



Nways Manager for AIX

Installation Guide

Version 2.0



Nways Manager for AIX

Installation Guide

Version 2.0

Note!

Before using this information and the product it supports, be sure to read the general information under "Chapter 7. Notices" on page 29.

Sixth Edition (May 1999)

This edition applies to Version 2.0 of the Nways Manager for AIX.

Order publications through your IBM representative or the IBM branch office serving your locality.

© **Copyright International Business Machines Corporation 1997, 1999. All rights reserved.**

US Government Users Restricted Rights – Use duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

| | |
|--|----|
| Chapter 1. Introduction | 1 |
| Try Nways Manager for 60 Days | 1 |
| SmoothStart | 1 |
| Automatic Alerts | 2 |
| Hardware and Software Prerequisites | 2 |
| | |
| Chapter 2. Installing Over Previous Versions | 3 |
| ObjectStore | 3 |
| Element Manager | 3 |
| Nways Manager ATM | 4 |
| Remote Monitor | 4 |
| Traffic Monitor | 4 |
| | |
| Chapter 3. Installing Nways Manager for AIX | 5 |
| Managing Licenses | 5 |
| Upgrading Your License | 6 |
| AIX 4.3 Upgrade Notes | 7 |
| Netview Fixes | 8 |
| | |
| Chapter 4. Configuring Nways Manager Applications | 9 |
| Java-Based Device Management | 9 |
| Accessing the Java-Based Device Manager Helps | 10 |
| About Device Configuration Programs | 10 |
| Accessing the Device Managers from a Web Browser | 11 |
| Remote Distributed Intelligent Agents (DIAs) | 13 |
| DB2 Universal Database | 14 |
| Stopping Automatic Polling | 16 |
| Web Server Settings | 18 |
| Apache Web Server | 18 |
| Netscape Web Server | 18 |
| Domino Web Server | 19 |
| Web Access for ATM Manager | 19 |
| Remote Monitor | 19 |
| Traffic Monitor | 20 |
| Nways Deployment Manager | 20 |
| | |
| Chapter 5. Starting Nways Manager for AIX | 21 |
| Starting Remote Monitor In Stand-Alone Mode | 21 |
| Starting Traffic Monitor In Stand-Alone Mode | 21 |
| Web Access to the ATM Manager | 22 |
| Accessing README Files | 22 |
| Accessing Online Documentation | 22 |
| Installing and Using Acrobat Reader 3.0 | 23 |
| | |
| Chapter 6. Removing Nways Manager Applications | 25 |
| Filesets | 25 |
| Log Files | 27 |

| | |
|---|----|
| Chapter 7. Notices | 29 |
| Trademarks | 30 |
| Readers' Comments — We'd Like to Hear from You | 31 |

Chapter 1. Introduction

IBM Nways[®] Manager for AIX[®] Version 2.0 provides an effective way to manage heterogeneous networks (ATM, token ring, Ethernet, FDDI), particularly LAN-based campus networks with high-speed backbones consisting of ATM and LAN switches.

Nways Manager consists of the following components, which are made up of applications:

- Element Manager
- Nways Manager ATM
- Remote Monitor
- Traffic Monitor
- VPN Manager

For a description of the Nways Manager for AIX Version 2.0, its components and applications, click on the blue **Information** icon on the Nways Manager for AIX Installation window of the Installation Program. This information is delivered in the CD-ROM.

For the latest technical information, including prerequisites and supported Web browsers, go to the Nways Management Web page:

<http://www.networking.ibm.com/netmgt>

Try Nways Manager for 60 Days

All Nways Manager components are provided on the CD-ROM that accompanies this book. You can install the Nways Manager Version 2.0 components and use them in a 60-day trial period. During (or after) this period, you may purchase any of the Nways Manager components.

When you purchase an Nways Manager component you receive a Production License Use Certificate (software key) that unlocks the component and allows you to permanently use it. You do not have to re-install the component or applications.

SmoothStart

SmoothStart[™] is an IBM service offering that provides on-site installation, configuration, integration, and education services for IBM networking devices and IBM Nways Manager for AIX. All information is available on the IBM Global Services Web site:

<http://www.as.ibm.com/asus/mus47ae.html>

Automatic Alerts

By signing up for automatic alerts, you will automatically receive e-mail notifying you of the latest news, fixes, and new releases for a variety of products of interest to users of the Nways Manager family of products.

You can sign up for automatic alerts on the Web at:

<http://www.networking.ibm.com/netsupt>

Hardware and Software Prerequisites

The Nways Manager installation process requires the installation of Java Development Kit (JDK) 1.1.6 or later. For information on hardware and software prerequisites for Nways Manager for AIX Version 2.0, visit our Web site at:

<http://www.networking.ibm.com/netmgt>

Chapter 2. Installing Over Previous Versions

If you are installing IBM Nways Manager for AIX Version 2.0 components over previous versions, follow the instructions in this chapter to maintain your current configuration.

ObjectStore

ObjectStore Version 5.1 is automatically installed when you install Nways Manager for AIX Version 2.0 Nways Manager ATM. If you already have ObjectStore Version 4.0 installed, you must modify the following parameters before installing the Element Manager components:

- The OS_ROOTDIR variable can be located in the following places:
 - /etc/environment
 - /etc/profile
 - your \$HOME/.profile

Locate the correct file, and edit the line that defines the OS_ROOTDIR variable to point to the new version of ObjectStore as shown:

```
export OS_ROOTDIR=/usr/lpp/ODI/OS5.1/cset
```

- In the /.profile file, delete \$OS_ROOTDIR/bin from the line that defines the PATH variable; for example:

```
export PATH=$PATH:$OS_ROOTDIR/bin
```

Element Manager

You cannot install the LAN component of Nways Manager for AIX Version 2.0 over a version of Nways Campus Manager LAN earlier than 3.2, which was shipped as part of Nways Manager for AIX Version 1.1. If you have previously installed Nways Campus Manager LAN Version 3.1 or earlier, you must completely uninstall it before installing the new Nways Manager product.

If you have installed Nways Campus Manager ATM Versions 1 or 2.1 on your management station, you must completely uninstall it before installing the new Nways Manager product.

You can install the LAN component of Nways Manager for AIX Version 2.0 over Nways Campus Manager LAN Version 3.2 or later if Nways Campus Manager ATM *is not* installed on the same workstation.

To remove the old Nways Campus Manager versions refer to the installation instructions that came with that version.

The Nways Manager for AIX Version 2.0 Element Manager component can operate only with IBM Nways Manager for AIX Version 2.0 Nways Manager ATM component that is provided with it.

Nways Manager ATM

You cannot install the ATM component of Nways Manager over any versions of Nways Campus Manager ATM older than 2.2, which was shipped as part of Nways Campus Manager ATM Version 1.1. Any earlier versions of this code, and the corresponding versions of Nways Campus Manager LAN must be completely uninstalled before installing Nways Manager for AIX 1.2.3.

Note that the ATM device element management that was previously included in Nways Campus Manager ATM was moved into the LAN component of Nways Manager for AIX beginning with Version 1.2.

To remove the old Nways Campus Manager versions refer to the installation instructions that came with that version.

The Nways Manager for AIX Version 2.0 Campus Manager - ATM component can only operate with IBM Nways Manager for AIX Version 2.0 Campus Manager - LAN component that is provided on this CD-ROM.

Remote Monitor

You can install Nways Manager for AIX Version 2.0 Remote Monitor component over all previous versions of Nways Campus Manager Remote Monitor or Nways Campus Manager Remote Monitor Advanced without losing your current configuration.

Traffic Monitor

You can install Nways Manager for AIX Version 2.0 Traffic Monitor component over Nways Traffic Monitor Version 1.1 (part of Nways Manager for AIX Version 1.1) without losing your current configuration.

Chapter 3. Installing Nways Manager for AIX

Note: The installation process for Nways Manager Version 2.0 requires that JDK 1.1.6 or later be installed on the target workstation.

To install Nways Manager for AIX Version 2.0, follow these steps:

1. Log in as the root user.
2. Make sure that you have stopped all the NetView daemons.
3. Create the mount point directory for the CD-ROM by entering the command:

```
mkdir /cdrom
```

Note: You *must* use /cdrom as the mount point. If you use a different mount point, the installation program will not work correctly.

4. Insert the IBM Nways Manager for AIX Version 2.0 CD-ROM into the CD-ROM drive.
5. Mount the CD-ROM by entering the command:

```
mount -r -v cdrfs /dev/cd0 /cdrom
```

6. Run the shell script to start the installation program by entering the command:
`/cdrom/install.nways`

The Welcome window for the installation program is displayed.

7. Follow the instructions in the installation program to select and install Nways Manager for AIX Version 2.0.

Important: Before you can remove a CD-ROM from the CD-ROM drive, you must first unmount the file system. To do so, enter the command:

```
umount /cdrom
```

Managing Licenses

If this is the first time you have installed Nways Manager for AIX Version 2.0, you will see the License screen that allows you to register your licensed products or elect to use a demonstration version of the installed Nways Manager components:

- To register a licensed product, enter your customer number and license key number when prompted.
- To install a 60-day demonstration version of the selected components, simply press **CTRL+C** to exit the License window. The trial installation will be completed automatically.

If you are installing the Element Management component or the Nways Manager Suite of components, you will be asked to select what version of these components you want to install and enter the number of nodes for which you have purchased a license.

If you have already installed some parts of the Element Manager component or the Nways Manager Suite, and have installed the correct license key, the installation program will complete automatically.

If you have not already installed an applicable license key, you will be taken to the License window to install the key and complete the installation.

Upgrading Your License

If you have purchased a license to upgrade from a demonstration version of an Nways Manager component, simply run the installation program again, select the component, and enter your customer number and license key number when prompted in the License window.

The key will be installed, the product will be registered, and you will not lose any of your accumulated data.

Increasing the Number of Licensed Nodes

If you have purchased a license allowing you to manage additional nodes using Nways Element Manager, use the following commands to update the node-count associated with your product license:

- If you have an Nways Element Manager license:

```
i4b1t -U -v "IBM Corporation" -p "Nways Mgr AIX Element Mgr 2.0" -T NUMNODES
```

where NUMNODES is the total number of nodes to support.

- If you have an Nways Manager Suite license:

```
i4b1t -U -v "IBM Corporation" -p "Nways Mgr AIX Suite' 2.0.N" -T NUMNODES
```

where NUMNODES is the total number of nodes to support.

Determining What Nodes to Monitor

Nways Manager determines what nodes to monitor by the contents of the file `nwaysjma.ini`. To remove nodes that you do not want to monitor and thus increase the number of other nodes you can monitor with your current license, you can edit this file and remove their entries.

To add nodes that you do want to monitor, edit the file and create entries for them. To do this, you must know their SYSOID.

A copy of this file is created when Nways Manager is installed and named `original.nwaysjma.ini`. To revert to your original configuration, rename this file `nwaysjma.ini`.

AIX 4.3 Upgrade Notes

If you plan to install or upgrade to AIX Version 4.3 on your Network Management station, be aware of the following:

After installing AIX Version 4.3 on your Network Management station, you must modify the LIBPATH environment variable to include the following path *at the beginning* of the LIBPATH:

```
/usr/lpp/X11/lib/R5:/usr/lpp/X11/lib/R5/Motif1.2
```

You must also ensure that if the directory /usr/Tivoli/lib/aix4-r1 is specified as part of the LIBPATH variable, it is the last directory specified, because this directory contains older copies of AIX system libraries that can cause applications not to run properly.

Modify the following files to include these changes:

- /etc/netnmrc
- /etc/Tivoli/setup_env.sh
- /usr/OV/bin/nv6000
- /usr/OV/bin/netview

Netview Fixes

Software fixes are available to enable you to run Netview on AIX 4.2.1 and 4.3.1. If you receive the following error messages:

On AIX 4.2.1

```
./netscape
exec(): 0509-036 Cannot load program /usr/net405/netscape_aix4 because of
the following errors:
0509-023 Symbol snprintf in /usr/lib/libX11.a is not defined.
0509-022 Cannot load library libXt.a[shr4.o].
0509-026 System error: Cannot run a file that does not have a valid form
```

On AIX 4.3.1

```
./netscape
exec(): 0509-036 Cannot load program /usr/netscape/t/net405/netscape_aix4 because of
the following errors:
0509-023 Symbol __malloc_postfork_unlock in /usr/lib/libpthreads.a is not defined
0509-023 Symbol __malloc_prefork_lock in /usr/lib/libpthreads.a is not defined
0509-022 Cannot load library libC.a[shr.o].
0509-026 System error: Cannot run a file that does not have a valid format
```

These fixes are available at:

<ftp://service.software.ibm.com/aix/efixes/netscape/>

Or from your IBM Service representative. Please consult the readme file that comes with the fixes for instructions on installation.

Chapter 4. Configuring Nways Manager Applications

This section describes any additional configuration steps that you need to perform after installing Nways Manager for AIX.

Java-Based Device Management

Nways Manager Element Manager supports the following IBM networking hardware:

- IBM Ethernet and Token-Ring Adapters
- MSS Client UFC in:
 - IBM 8270 Nways LAN Switch
 - IBM 8272 LAN Switch Modules
- IBM Network Utility
- MSS Domain Client UFC in:
 - IBM 8270 Nways LAN Switch
 - IBM 8272 Nways Token-Ring LAN Switch model 216
 - IBM 8271 and 8272 2- and 3-slot LAN Switch Modules
- IBM 2210 Nways Multiprotocol Router
- IBM 2212 Access Utility
- IBM 2216 Multiaccess Connector
- IBM 8210 Nways Multiprotocol Switched Services (MSS) Server
- IBM 8224 Ethernet Stackable Hub
- IBM 8225 Fast Ethernet Stackable Hub
- IBM 8229 Bridge
- IBM 8230 Token Ring Network Controlled Access Unit
- IBM 8237 Stackable Ethernet Hub
- IBM 8238 Token Ring Stackable Hub
- IBM 8239 Token Ring Stackable Hub
- IBM 8245 Nways 10/100 Ethernet Stackable Hub
- IBM 8250 Multiprotocol Intelligent Hub
- IBM 8260 Nways Multiprotocol Switching Hub
- IBM 8265 Nways ATM Switch
- IBM 8270 Nways LAN Switch Family
- IBM 8271 Nways Ethernet LAN Switch, models E12, E24, F12, F24, 108, 212, 412, 216, 524, 612, 624, and 712
- IBM 8272 Nways Token-Ring LAN Switch
- IBM 8273 Nways Ethernet RouteSwitch
- IBM 8275 Nways Ethernet LAN Switch
- IBM 8281 Nways ATM LAN Bridge
- IBM 8282 Nways ATM Workgroup Concentrator

- IBM 8285 Nways ATM Workgroup Switch
- IBM 8371 Multilayer Ethernet Switch
- Generic Java™-based management for any SNMP-enabled device in your network.

Note: For the most up-to-date information on hardware supported by Nways Manager Element Manager, see our Web page at:

<http://www.networking.ibm.com/netmgt>

These device managers consist of Nways Web pages (both HTML and Java) and can be used at the local management workstation or from JDK 1.1.5-compliant Web browsers running on any platform from anywhere in your enterprise.

Accessing the Java-Based Device Manager Helps

The Java-based managers use a Web browser to display their HTML help panels. If the Web browser is installed in a directory that is not included in the search path, then you will not be able to access the online help. The installation program assumes that you are using Netscape as your Web browser.

To use a Web browser other than Netscape or to specify a browser that is not in the search path, edit the `/usr/CML/JMA/java/websvr/properties/BrowserApplet.txt` file and specify the fully qualified name for the Web browser on the following line:

```
webBrowser.path=
```

About Device Configuration Programs

Some IBM networking products include a configuration program. Nways Manager allows you to launch these configuration programs from the device's JMA.

In order to launch the configuration program from the JMA, Nways Manager must know the location of the configuration tool on the network management workstation. For configuration tools shipped after July 1998, this information is automatically updated when the configuration tool is installed.

To locate older versions of configuration tools, Nways Manager includes the Config Tool Locator, which locates existing versions of configuration tools already installed on the network management workstation. You should run the Config Tool Locator when you install Nways Manager, and again after each installation of a configuration tool that originally shipped prior to July 1998.

To run the config tool locator, from SMIT, select

Nways Campus Manager->Configure->Config Tool Locator

If the Config Tool Locator is unable to find a configuration tool that is loaded on the network management workstation, you can add the location of the program to the list of known programs using the following procedure:

1. Locate the correct configuration tool (cfg.exe or cfg.app file) on the network management workstation and note the file size.
2. Check the Config Tool Locator's FixCfg.properties file (located in the directory /usr/CML/JMA/java/fixcfg) to ensure that the size of this configuration tool is unique.
3. Add a new entry to the FixCfg.properties file, using existing entries as a model.
4. Rerun the Config Tool Locator
5. Restart the JMA

Accessing the Device Managers from a Web Browser

There are three basic components involved in Web browser-based access to the device managers:

- Nways Manager Workstation
- Web Server
- Web Browser compliant with JDK 1.1.5 or later

Nways Manager Workstation

The Nways Manager maintains the Nways Web pages that are sent from the Web server to the Web browser clients.

Web Server

You can run Java device management applications in client mode on stations connected to the network management station without configuring a Web server, but for true intranet access through a Web browser, you must configure your Web server to locate the Nways Java Management Web pages subdirectory.

Web servers supported for the Nways Web access include:

- IBM Internet Connection Secure Server
- Lotus® Domino™ Go Server
- Netscape Enterprise Server

On the network management station, you must:

1. Assign a new port number for use by the HTTP server higher than 8000. (The default value is 80.) This action adds an additional level of security to Web browser access, and prevents port conflicts with other applications using the server.
2. Assign an alias or logical name to the directory in which the HTML pages are stored on the management system. The Nways Web pages are stored in:
/usr/CML/JMA/java/websvr.
3. Verify that the properties assigned to this directory by the server include allowing Web browser access. Consult your Web server documentation for more information on how to do this.

Web Access for ATM Manager

Before you can use the ATM Manager via a Web browser, you must configure your Web server. The following configuration for the Lotus Domino server can be used as a guide if you are using another server.

1. Enter the following commands in the configuration file of your Web server, making sure that the two "Pass" statements are entered in this order:

```
Exec      /atm-bin/*      /usr/CML/ATMWEB/bin/*
Pass      /atm-html/*    /usr/CML/ATMWEB/html/*
Pass      /*       /a directory path/*
```

2. Reset the Web server by entering the appropriate command; for example:

```
refresh -s httpd
```

Web Browser Compliant with JDK 1.1.5 or Later

Java support comes with your browser. The Web browser can dynamically load the Java application.

Java communication uses the IP host name and not the IP address, therefore both the client and server need the correct host names to which they are communicating. If the client is dynamically assigned an IP address, ensure that this IP address is associated with your client's IP host name. This process works correctly with Dynamic Host Configuration Protocol (DHCP).

If your client uses the PPP protocol to connect to the server, the client will be dynamically assigned both an IP address and an IP host name. In this situation, Windows[®] 3.x, Windows NT[®], or Windows 95) do not provide the correct IP host name to the Java applications running in the client. Hence, the Java applications will not provide the correct IP host name to the server and the server will not be able to send asynchronous (unsolicited) events to the client. To correct this problem, change the IP host name on the Windows client to the value "localhost" for the PPP connection's TCP/IP protocol. The Java code in the Windows client will then provide the server with the correct (dynamically assigned) IP host name.

When you access the Nways Web pages, your browser may ask if you want to allow unsigned applets. To use the Web functions of the Nways Manager, you must allow unsigned applets.

Note: If you are using the HotJava[™] Browser, you must start it using the following parameters:

```
hotjava -mx64M
```

Remote Distributed Intelligent Agents (DIAs)

The Element Manager provides DIAs that can be placed in remote Java-enabled workstations to off-load performance management polling for these device managers.

The recommended JDK for use with the DIAs is 1.1.6.

Refer to the following readme file for complete instructions:

```
/usr/CML/JMA/dia/readme.txt
```

DB2 Universal Database

Performance management for these device managers uses a Java Database Connectivity (JDBC)-compliant database. For your convenience, DB2 Universal Database® is provided.

You will need to create a database instance that can be accessed using JDBC by the device managers. The following steps show how to do this using DB2® (the concept is the same if you are using another JDBC-compliant database, but you will need to refer to that database's instructions): Before installing DB2, create the following AIX group and user definitions using the **SMIT -> Security and Users** menu:

- **Group: nwaysdb2**

This group will be used for the DB2 Instance and Administrative Server.

Using SMIT, the Add Group menu requires the name to be entered first. After entering the name, set the Administrative Group field to True.

- **User: nwaysdb2**

This is the DB2 Instance Owner.

Using SMIT, enter the name of the user to be added first, then complete only the following fields:

```
ADMINISTRATIVE USER = true
Primary group = nwaysdb2
Group SET = nwaysdb2,system
ADMINISTRATIVE GROUP = nwaysdb2
```

- **User: nwaysadm**

This is the owner of the Administrative Server. This value is optional.

Follow the same steps used to define the user nwaysdb2, using the user name nwaysadm.

- **User: root**

Modify the existing user definition for root to add nwaysdb2 to the Group SET.

After you have completed these changes, use the following commands to confirm the correct settings of the new group and users:

```
lsgroup nwaysdb2
lsgroup system
```

All three users should show up as users in both groups.

1. After you have created these users, select passwords for them and log in as each user to change the temporary status of the root-generated ones. You will need these passwords when configuring DB2, so be sure to write them down.
2. To begin the installation, mount the CD using the following command:

```
mount -r -v cdrfs /dev/cd0 /mnt
```

You can install using SMIT or the db2setup script included on the CD. Installing using the script assists you in selecting the components to install and allows you to set up users during installation.

3. Change directory to the mount point and run the script db2setup.
Select the Universal Enterprise Database option to install. You can select only one major product group.
Use the spacebar to choose options. When you have completed a panel click **OK**.
4. After the installation is set up, you are asked whether you want to create the Instance and Administrative Server. Select Instance, then click **Customize** to set up the server. For the Instance user, use nwaysdb2 as the user name, nwaysdb2 as the group, and the password you configured earlier.
Click **OK** when you are done.
5. You are then prompted to configure another user. Enter the same user you entered above. This is referred to as the fence user.
6. Use the same procedure to configure the Administrative Server, using nwaysadm as the user name and nwaysdb2 as the group.
7. After creating the user, check the ownership of the nwaysdb2.profile. If ownership is not assigned correctly, logon as root and change the ownership of the \$HOME/.profile:

```
cd /home/nwaysdb2
chown nwaysdb2:nwaysdb2 .profile
```

Note: The next two steps refer to the application of a PTF to DB2. You must apply this PTF before configuring DB2 for use with Nways Manager.

If you choose not to install the PTF now, you can skip the next two steps and complete the installation. If you install the PTF at a later date, you must then rebind the DB2 files.

8. If you are using Version 5 of IBM DB2 Universal Database, you must use release 2 or later (Version 5.2 or later). If you received Version 5.0 with Nways Manager, apply FixPak 6 to upgrade to Version 5.2. You may also want to apply subsequent FixPaks as a maintenance measure.
In the United States and Canada, call 1–800–237–5511 to request the DB2 APAR. Outside the United States and Canada, contact your country support representative.
You can also download the APAR at:
<http://www.software.ibm.com/data/db2/db2tech/version5.html>
9. Add the following line to nwaysdb2's profile after the existing PATH statements:

```
. sqllib/db2profile
```
10. Activate the new profile using the .profile command.
11. Execute the following command to automatically start the instance on reboots:

```
db2set -i nwaysdb2 DB2AUTOSTART=YES
```
12. Start the DB2 instance:

```
db2start
```
13. Start the Command Line Processor (CLP):

```
db2
```
14. At the CLP prompt, enter:

CREATE DATABASE IBMNMPDB

15. After the database is successfully created, enter:
QUIT
 16. Log in as root and, if the directory /usr/CML/JMA/java/websvr/code was not created during Nways Manager Installation, create it.
 17. Move the DB2 JDBC drivers into the Nways class path using the following commands:

```
cd /usr/CML/JMA/websvr/code
jar -xvf /usr/lpp/db2_05_00/java/db2java.zip
```
 18. Modify the existing PATH statement in /etc/environment to include:

```
PATH=/home/nwaysdb2/sql1lib/bin:/home/nwaysdb2/
sql1lib/adm:/home/nwaysdb2/sql1lib/misc
```
 19. Add the following lines to /etc/environment:

```
DB2DIR=/usr/lpp/db2_05_00
DB2INSTANCE=nwaysdb2
LD_LIBRARY_PATH=/home/nwaysdb2/sql1lib/lib
```
 20. In /etc/inittab, move the following line:

```
rcdb2:2:once:/etc/rc.db2 > /dev/console 2>script
```

immediately before the line equivalent to:

```
rctcpip:2:wait:/etc/rc.tcpip > /dev/console 2>script
```
 21. Reboot the machine for the modifications to take effect.
 22. Ensure that the Nways Manager daemons are running and then start the Nways Manager Performance Management Configuration application by selecting **IBM Nways Java->Performance Configuration** from the NetView Tools menu, or by issuing the following command:

```
/usr/CML/JMA/bin/dpadmin
```
 23. From the Performance Management Configuration window, select the Database tab. There are 4 fields in this window. Two are filled for DB2. The third and fourth fields are UserId and Password, which can be ignored.

The dpadmin and dpconfig screens show the polling list, templates, reports, and other features. Once the collection is started, you can close this window and the collection will continue running. To stop the collection, reopen this window and click on **Stop Collection**.
- In addition to DB2, IBM has successfully tested JPM with the following databases:
- Oracle
 - Sybase

Stopping Automatic Polling

If you do not need to collect performance statistics, you can reduce the workload of the Nways Manager workstation and eliminate some network traffic by turning off performance polling.

To do this:

1. Stop the JMA server using the command:

ovstop JMAintegrator

2. Edit the file `/usr/CML/JMA/java/properties/JdmServerProperties.txt` to change the section:

```
# The services property identifies the service classes to be started
# when the JDM server is started.
#      ibm.nways.jdm.TrapCatcher           \
services=ibm.nways.jdm.RemoteModelFactoryManager \
      ibm.nways.jdm.modelgen.InstrContextFactoryMgr \
      ibm.nways.jdm.SnmpService           \
      ibm.nways.jdm.browser.BrowserService \
      ibm.nways.perfhook.PerfService      \
      ibm.nways.jdm.traceroute.TraceRouteService \
      ibm.nways.perfhook.ModelListener
```

to:

```
# The services property identifies the service classes to be started
# when the JDM server is started.
#      ibm.nways.jdm.TrapCatcher           \
#      ibm.nways.perfhook.PerfService      \
services=ibm.nways.jdm.RemoteModelFactoryManager \
      ibm.nways.jdm.modelgen.InstrContextFactoryMgr \
      ibm.nways.jdm.SnmpService           \
      ibm.nways.jdm.browser.BrowserService \
      ibm.nways.jdm.traceroute.TraceRouteService \
      ibm.nways.perfhook.ModelListener \
```

3. Save the file.
4. Restart the JMA server using the command:

ovstart JMAintegrator

In addition to minimizing both network traffic and the size of your performance database, stopping automatic polling will have these effects:

- No performance polling is done for newly or previously managed devices.
- Performance bullets in the JMA navigation tree will be blue (status=unknown).
- Clicking on the performance bullets will result in a panel containing only the performance toolbar.
- You will receive several "Cannot find PollingService" messages in your log files.

To restore automatic polling, reverse the changes described above to return the JdmServerProperties.txt file to its original state.

Note: Over-polling devices can result in degradation of performance for both the device and the device-management application. If you encounter these types of performance degradation, review your polling configuration.

Web Server Settings

All the Web servers have to be configured to listen to the client on port 80 (the default port in most of the servers).

Apache Web Server

Add the following lines in the given order to the file:

```
/Server_root/conf/srm.conf.  
Alias /nways "/Nways_root/CML/JMA/java/websvr"  
Alias /cgi/code "/Nways_root/CML/JMA/java/websvr/code"  
ScriptAlias /cgi "/Nways_root/CML/JMA/java/websvr"
```

Server_root: The directory where the Apache Websvr is installed.

Nways_root: The directory where the Nways product is installed.

Netscape Web Server

1. Go to the server main page and check whether the Server is ON.
2. Select **Programs** menu from the top of the page.
 - a. Select **CGI File Type**.
 - b. Select **Yes** for Activate CGI as a file type.
3. Select **Content Management** from the top menu.

Select **Additional Document Directories** and add the following lines:

```
URL prefix: nways  
Map To Directory: /Nways_root/CML/JMA/java/websvr  
  
URL prefix: cgi  
Map To Directory: /Nways_root/CML/JMA/java/websvr
```


Domino Web Server

1. Go to
`http://Machine/Frntpage.html`

(Machine—where you have installed the Domino Web Server.)
2. Select **Configuration and Administration Forms**
(`http://Machine/admin-bin/Cfgin/initial`)
3. Select **Request Routing**
(`http://Machine/admin-bin/Cfgin/mpfrule`)
4. Add the following lines in the given order:

| Action | Request Template | Replacement File Path |
|--------|--------------------------------|---|
| Pass | <code>/nways/*</code> | <code>/Nways_root/CML/JMA/java/websvr/*</code> |
| Exec | <code>/cgi/CgiLauncher*</code> | <code>/Nways_root/CML/JMA/java/websvr/CgiLauncher*</code> |
| Pass | <code>/cgi/*</code> | <code>/Nways_root/CML/JMA/java/websvr/*</code> |

Web Access for ATM Manager

Before you can use the ATM Manager via a Web browser, you must configure your Web server as follows:

1. Enter the following commands in the configuration file of your Web server, making sure that the two “Pass” statements are entered in this order:

```
Exec      /atm-bin/*      /usr/CML/ATMWEB/bin/*
Pass      /atm-html/*    /usr/CML/ATMWEB/html/*
Pass      /*       /a directory path/*
```

2. Reset the Web server by entering the appropriate command; for example:

```
refresh -s httpd
```

Remote Monitor

Before you can use Remote Monitor, you must set the RMONHOME environment variable to point to the directory where it has been installed. It is installed by default in `/usr/LANReMon/rmon`. To set the RMONHOME environment variable in your `.profile` and add it to your default path, add the following to your `.profile`:

```
RMONHOME=/usr/LANReMon/rmon
export RMONHOME
PATH=$RMONHOME:$PATH
export PATH
```

Traffic Monitor

Before you can use Traffic Monitor, you must set the TRAFFICMONHOME environment variable to point to the directory where it has been installed. It is installed by default in /usr/LANReMon/trafficmon. To set the TRAFFICMONHOME environment variable in your .profile and add it to your default path, add the following to your .profile:

```
TRAFFICMONHOME=/usr/LANReMon/trafficmon
export TRAFFICMONHOME
PATH=$TRAFFICMONHOME:$PATH
export PATH
```

Before starting Traffic Monitor, you must also create the following database:

```
/usr/LANReMon/trafficmon/tfm_dbcreate <db_dir> <db_link>
ln -s <db_dir>.dbs /usr/LANReMon/trafficmon/<db_link>.dbs
```

Where <db_dir> is the directory where the database will be stored, and <db_link> is the name of the database and the name of the link that must be created in the /usr/LANReMon/trafficmon directory.

The <db_link> is normally **tfm** and the actual link name is **tfm.dbs**.

Nways Deployment Manager

Nways Deployment Manager requires the creation of a DB2 database with a database name, user ID, and password all set to ConfigMan.

Chapter 5. Starting Nways Manager for AIX

The first time you start an application, be sure to log in as a root user. To start the Nways Manager applications that you have installed, enter the command:

```
nv6000
```

The NetView root map is displayed, from which you can open Nways Manager applications.

- **To open Element Manager:**
 - Click on NetView root map “Hubs Topology” icon to display the IBM Hubs topology.
 - Click on NetView root map “LAN” icon to display the LAN Network submap.
 - Click on NetView root map “Router and Bridge Manager” icon to open the Router and Bridge Manager.
 - Click the Nways Device Management icon to display the Device Manager topology.
- **To open Nways Manager ATM:**
 - Click on the “ATM Campus” icon to display the ATM topology.
 - Click on the “VLANs” icon to use the LAN-Emulation function.
- To open Remote Monitor, select from the NetView menu bar **Monitor->Nways Manager-Remote Monitor->Nways Manager-Remote Monitor Tools**
- To open Traffic Monitor, from the NetView menu bar, select **Monitor->IBM Traffic Monitor->Start Traffic Monitor** and then select **Monitor->IBM Traffic Monitor->Start Map**

You can also run Remote Monitor and Traffic Monitor in stand-alone mode without starting NetView.

Starting Remote Monitor In Stand-Alone Mode

To run Remote Monitor in stand-alone mode, enter:

- **\$RMONHOME/rmon**

Starting Traffic Monitor In Stand-Alone Mode

To run Traffic Monitor in stand-alone mode, do the following:

- To start the Collector, enter:
 - **cd \$TRAFFICMONHOME**
 - **./trafficmon start**
- To start the Map, enter:
 - **cd \$TRAFFICMONHOME**
 - **./trafficmon map**

- To start Error Log Monitor, enter:
 - `cd $TRAFFICMONHOME`
 - `./trafficmon log`

Web Access to the ATM Manager

To use your Web browser to access the ATM Manager function, use the following Web page:

`http://hostname/atm-htm1/AtmWebMngt.html`

where *hostname* is the AIX station where you installed the ATM Manager with Web access support.

Accessing README Files

You can elect to view the README files as part of the Installation process. The following README files are also installed:

| Component | README File |
|--------------------------------------|---|
| Element Manager | <code>/usr/lpp/cml/lpp.README</code> |
| Distributed Intelligent Agent | <code>/usr/CML/JMA/dia/readme.txt</code> |
| Nways Manager ATM | <code>/usr/lpp/ahm6000/lpp.README</code> |
| Remote Monitor | <code>/usr/lpp/lanReMon/lpp.README</code> |
| Traffic Monitor | <code>/usr/lpp/trafficMon/lpp.README</code> |
| VPN Manager | |
| Nways Deployment Manager | |

Information about how to use ObjectStore is located in the file:

`/usr/lpp/ODI/OS5.0/common/doc/mo/index.htm`

Accessing Online Documentation

After starting Nways Manager, you can access online User's Guides for Nways Manager applications:

Element Manager Online Documentation

- Select **Help -> Element Manager User's Guide** to access online documentation for the following applications:
 - 8250 Multiprotocol Intelligent Hub Device Manager
 - 8260 Nways Multiprotocol Switching Hub Device Manager
 - 8265 Nways ATM Switch Device Manager

FDDI Management using 8244 FDDI Workgroup Concentrator
SNMP Bridge/Switch Manager
Token-Ring Management accessing LAN Network Manager for OS/2
Token-Ring Management using SNMP Token-Ring Devices

- Use the Acrobat Reader 3.0 to access online documentation of the IBM 8260 LAN Switching Modules Series, available under directory
`/usr/CML/doc/cm1.nsmm.pdf`
- Select **Help->IBM Device Managers User's Guide** to access online documentation for:
 - 8224 Ethernet Stackable Hub Device Manager
 - 8225 Fast Ethernet Stackable Hub Device Manager
 - 8230 Token-Ring Controlled Access Unit Device Manager
 - 8235 Dial-In Access to LANs (DIALs) Server Device Manager
 - 8238 Token-Ring Stackable Hub Device Manager
 - 8273/8277 Nways Ethernet RouteSwitch Device Manager
 - 8274 Nways LAN RouteSwitch Device Manager
 - 8276 Nways Ethernet RoutePort Device Manager
 - 8281 Nways ATM LAN Bridge Device Manager
 - 8282 Nways ATM Workgroup Concentrator Device Manager
 - 8285 Nways ATM Workgroup Switch Device Manager

Nways Manager ATM Online Documentation

- Select **Help->Nways Manager->ATM User's Guide** to access online documentation for the following applications:
 - ATM Manager
 - LAN Emulation Manager

Remote Monitor and Traffic Monitor Online Documentation

- Use the Acrobat Reader 3.0 to access online documentation for Remote Monitor and Traffic Monitor, available in directories:
 - `/usr/LANReMon/doc/ecam.pdf`
 - `/usr/LANReMon/doc/ttmm.pdf`
 - `/usr/LANReMon/doc/lanremon.pdf`
 - `/usr/LANReMon/doc/trafficMon.pdf`

Installing and Using Acrobat Reader 3.0

Acrobat Reader 3.0 is provided on the CD-ROM. To install it:

1. Untar file `aixreader.tar` located in `/cdrom/acrobat` using the following command:

```
tar -xvf aixreader.tar
```
2. Uncompress the resulting file.
3. Type `INSTALL` and follow the procedure.
4. When prompted, enter the Installation directory. By default it is

```
/usr/lpp/Acrobat3
```

5. Update your .profile with the Acrobat Reader installation directory:

```
export PATH=$PATH:/usr/lpp/Acrobat3/bin
```

To start Acrobat Reader 3.0 enter **acroread** then select the directory where the documentation you are looking for is stored.

Chapter 6. Removing Nways Manager Applications

To remove Nways Manager applications, follow these steps:

1. Log in as the root user.
2. Make sure that you have stopped all NetView daemons.
3. At the prompt, enter `smit`.
4. From the SMIT main menu, click **Communications**.
5. Select **Nways Campus Manager**.
6. Select **Maintain**.
7. Select **Campus Manager general maintenance**.
8. Select **Remove Nways Campus Manager Software**.

If you want remove selected components, use the option that appears under the **Campus Manager general maintenance** menu.

Note: This procedure will not remove the Router and Bridge Manager component of Nways Campus Manager LAN, nor will it remove the Nways Remote Monitor. To remove these applications:

1. Log in as the root user.
2. Make sure that you have stopped all the NetView daemons.
3. At the prompt, enter `smit`.
4. From the SMIT main menu, click **Software Installation and Maintenance**. The Software Installation and Maintenance menu is displayed.
5. Select **Maintain Installed Software**.
6. Select **Remove Software Products**.
7. In the Remove Software Products window, select the filesets for the component you want to remove and then select **OK**. Filesets are listed on the following page.
8. Select **Exit -> Exit SMIT** from the menu bar to exit SMIT.

During the removal procedure, the removal and de-configuration steps are displayed in the SMIT window. These steps are logged in the `smit.log` file and in the log files for each component. See "Log Files" on page 27.

Filesets

In order to remove (uninstall) Nways Manager for AIX Version 2.0 applications, you must specify the filesets in each component.

License Fileset - Shared By All Components

The license fileset: `cml.license.cat` is used by all components of Nways Manager. ***Do not remove this fileset unless you are deinstalling the entire product.***

Element Manager Filesets

alertman.obj
cml.baseLan
cml.books
nwaysmgr.jma
ahm6000.base.msg.En_US
cml.br
cml.fddi
cml.Jjim
cml.Jjim.msg.En_US
smcfg.dtext.En_US.eui.obj
cml.license.ncml
smcfg.eui.obj
cml.lnme
smmlm.subagent.obj
cml.tr
cml.baseLan.msg.En_US
cml.br.msg.En_US
cml.fddi.msg.En_US
cml.lnme.msg.En_US
cml.tr.msg.En_US
nwaysmgr.jma.msg.En_US
cml.8250-60
cml.8250-60.msg.En_US

Campus Manager - ATM Filesets

| | |
|--------------------------|------------------|
| ahm6000.atmweb | cml.Jfault |
| ahm6000.atmweb.msg.En_US | cml.Jpnni |
| ahm6000.base | cml.jvnet |
| ahm6000.base.msg.En_US | cml.license.ncma |
| ahm6000.books.En_US.base | cml.vnet |

Common Filesets Shared By Nways Manager ATM and Element Manager

cml.base
cml.base.msg.En_US
ostore_runtime.base
cml.Jcomm
cml.Jcomm.msg.En_US

Remote Monitor Filesets

| | |
|----------------------|----------------------|
| cml.license.rmon | lanReMon.base.obj |
| lanReMon.advance.obj | lanReMon.En_US.books |

Traffic Monitor Filesets

| | |
|------------------------|------------------------|
| cml.license.traffic | trafficMon.traffic_Mon |
| trafficMon.En_US.books | |

Common Filesets Shared By Remote Monitor and Traffic Monitor

rmonCommon.rmon_Common

Log Files

Table 1. Log Files for Nways Manager for AIX Version 2.0 Components

| Component and Directories | Log Files |
|--|---|
| Element Manager log files are available in directories: /usr/CML/install_log /usr/CML/deinstall_log | cml.base.log cml.baseLan.log cml.books.log cml.br.log cml.fddi.log cml.lnme.log cml.smm.log cml.tr.log nwaysmgr.jma.log |
| Nways Manager ATM log files are available in directories: /usr/CML/install_log /usr/CML/deinstall_log | ahm6000.base.log cml.base.log |
| Remote Monitor log files are available in directories: /usr/LANReMon/install_log /usr/LANReMon/deinstall_log | lanReMon.base.obj.log lanReMon.advance.obj.log rmonCommon.rmon_Common.log |
| Traffic Monitor log files are available in directories: /usr/LANReMon/install_log /usr/LANReMon/deinstall_log | trafficMon.traffic_Mon.log rmonCommon.rmon_Common.log |

Chapter 7. Notices

This information was developed for products and services offered in the U.S.A. IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area.

References in this publication to IBM products, programs, and services do not imply that IBM intends to make these available in all countries in which IBM operates. Any reference to an IBM product, program, or service is not that only IBM's product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any of IBM's intellectual property rights may be used instead of the IBM product, program, or service. Evaluation and verification of operation in conjunction with other products, except those expressly designated by IBM, are the user's responsibility.

IBM may have patents or pending patent applications covering the subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10504-1785
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law: INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY, OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

Trademarks

The following terms are trademarks of International Business Machines Corporation in the United States or other countries or both:

| | | |
|-------|------------------------|------------|
| AIX | DB2 Universal Database | AIXwindows |
| DB2 | IBM | APPN |
| Nways | SmoothStart | OS/2 |

NetView and TME 10 are trademarks of Tivoli Systems, Inc. in the United States or other countries or both.

Domino and Lotus are trademarks of Lotus Development Corporation in the United States or other countries or both.

Java and all Java-based trademarks and logos are trademarks of Sun Microsystems, Inc. in the United States and/or other countries.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks or registered trademarks of Microsoft Corporation.

UNIX is a registered trademark in the United States and other countries licensed exclusively through X/Open Company Limited.

Other company, product, and service names may be trademarks or service marks of others.

Readers' Comments — We'd Like to Hear from You

**Nways Manager for AIX
Installation Guide
Version 2.0**

Overall, how satisfied are you with the information in this book?

| | Very Satisfied | Satisfied | Neutral | Dissatisfied | Very Dissatisfied |
|----------------------|--------------------------|--------------------------|--------------------------|--------------------------|--------------------------|
| Overall satisfaction | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |

How satisfied are you that the information in this book is:

| | Very Satisfied | Satisfied | Neutral | Dissatisfied | Very Dissatisfied |
|--------------------------|--------------------------|--------------------------|--------------------------|--------------------------|--------------------------|
| Accurate | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |
| Complete | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |
| Easy to find | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |
| Easy to understand | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |
| Well organized | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |
| Applicable to your tasks | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> | <input type="checkbox"/> |

Please tell us how we can improve this book:

Thank you for your responses. May we contact you? Yes No

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

Name

Address

Company or Organization

Phone No.

Readers' Comments — We'd Like to Hear from You



Cut or Fold
Along Line

Fold and Tape

Please do not staple

Fold and Tape

PLACE
POSTAGE
STAMP
HERE

Department CGFA
Design & Information Development
IBM Corporation
PO Box 12195
RESEARCH TRIANGLE PARK, NC 27709

Fold and Tape

Please do not staple

Fold and Tape

Cut or Fold
Along Line



Part Number: CT7SJNA

Printed in U.S.A

CT7SJNA

