MATLAB® 7 Function Reference: Volume 3 (P-Z)

MATLAB®



How to Contact The MathWorks



(a)

www.mathworks.comWebcomp.soft-sys.matlabNewsgroupwww.mathworks.com/contact_TS.htmlTechnical Support

suggest@mathworks.com bugs@mathworks.com doc@mathworks.com service@mathworks.com info@mathworks.com Product enhancement suggestions Bug reports Documentation error reports Order status, license renewals, passcodes Sales, pricing, and general information



508-647-7001 (Fax)

508-647-7000 (Phone)

The MathWorks, Inc. 3 Apple Hill Drive Natick, MA 01760-2098

For contact information about worldwide offices, see the MathWorks Web site.

MATLAB Function Reference

© COPYRIGHT 1984–2010 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227.7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See www.mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

Patents

The MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

Revision History

December 1996 June 1997 October 1997 January 1999 June 1999 June 2001 July 2002 June 2004 September 2006 March 2007 September 2007 March 2008 October 2008 March 2009 September 2009 March 2010

First printing Online only Online only Online only Second printing Online only Online only

For MATLAB 5.0 (Release 8) Revised for MATLAB 5.1 (Release 9) Revised for MATLAB 5.2 (Release 10) Revised for MATLAB 5.3 (Release 11) For MATLAB 5.3 (Release 11) Revised for MATLAB 6.1 (Release 12.1) Revised for 6.5 (Release 13) Revised for 7.0 (Release 14) Revised for 7.3 (Release 2006b) Revised for 7.4 (Release 2007a) Revised for Version 7.5 (Release 2007b) Revised for Version 7.6 (Release 2008a) Revised for Version 7.7 (Release 2008b) Revised for Version 7.8 (Release 2009a) Revised for Version 7.9 (Release 2009b) Revised for Version 7.10 (Release 2010a)



Function Reference

Desktop Tools and Development Environment	1-3
Startup and Shutdown	1-3
Command Window and History	1-4
Help for Using MATLAB	1-5
Workspace	1-5
Managing Files	1-0
	1-0
Programming Tools	
System	1-10
Data Import and Export	1-12
File Name Construction	1-12
File Opening, Loading, and Saving	1-13
Memory Mapping	1-13
Low-Level File I/O	1-14
Text Files	1-14
XML Documents	1-15
Spreadsheets	1-15
Scientific Data	1-16
Audio and Video	1-24
Images	1-24
Internet Exchange	1-26
	1-20
Mathematics	1-28
Arrays and Matrices	1-29
Linear Algebra	1-34
Elementary Math	1-38
Polynomials	1-43
Interpolation and Computational Geometry	1-43
Cartesian Coordinate System Conversion	1-47
Nonlinear Numerical Methods	1-47
Specialized Math	1-51
Sparse Matrices	1-52
Math Constants	1-55
Data Analysis	1-57
Data 1111a1 y 515	1-01

1 [

Basic Operations	1-57
Descriptive Statistics	1-57
Filtering and Convolution	1-58
Interpolation and Regression	1-58
Fourier Transforms	1-59
Derivatives and Integrals	1-59
Time Series Objects	1-60
Time Series Collections	1-63
Programming and Data Tunag	1-65
Programming and Data Types	1-65 1-65
Data TypesData Type Conversion	1-05
Operators and Special Characters	1-74
	1-70
Strings Bit-Wise Operations	1-78
	1-81
Logical Operations	1-82 1-82
	1-82 1-83
Set Operations	1-83
Date and Time OperationsProgramming in MATLAB	1-83 1-84
Programming in MAILAD	1-84
Object-Oriented Programming	1-92
Classes and Objects	1-92
Handle Classes	1-93
Events and Listeners	1-94
Meta-Classes	1-94
Cranhia	1-96
Graphics	1-96
Basic Plots and Graphs	1-90 1-97
Plotting Tools	1-97 1-97
Annotating Plots	1-97
Specialized Plotting	
Bit-Mapped Images	1-101
Printing	1-102
Handle Graphics	1-102
3-D Visualization	1-107
Surface and Mesh Plots	1-107
View Control	1-109
Lighting	1-111
Transparency	1-111
Volume Visualization	1-111

GUI Development	1 - 113
Predefined Dialog Boxes	1-113
User Interface Deployment	1-114
User Interface Development	1-114
User Interface Objects	1-115
Objects from Callbacks	1-116
GUI Utilities	1-116
Program Execution	1-117
External Interfaces	1-118
External Interfaces	-
	-
Shared Libraries	1-118
Shared LibrariesJava	1-118 1-119
Shared Libraries Java .NET	1-118 1-119 1-120 1-121
Shared Libraries Java .NET Component Object Model and ActiveX	1-118 1-119 1-120 1-121 1-123

Alphabetical List

2

Index

Function Reference

Desktop Tools and Development Environment (p. 1-3)	Startup, Command Window, help, editing and debugging, tuning, other general functions
Data Import and Export (p. 1-12)	General and low-level file I/O, plus specific file formats, like audio, spreadsheet, HDF, images
Mathematics (p. 1-28)	Arrays and matrices, linear algebra, other areas of mathematics
Data Analysis (p. 1-57)	Basic data operations, descriptive statistics, covariance and correlation, filtering and convolution, numerical derivatives and integrals, Fourier transforms, time series analysis
Programming and Data Types (p. 1-65)	Function/expression evaluation, program control, function handles, object oriented programming, error handling, operators, data types, dates and times, timers
Object-Oriented Programming (p. 1-92)	Functions for working with classes and objects
Graphics (p. 1-96)	Line plots, annotating graphs, specialized plots, images, printing, Handle Graphics
3-D Visualization (p. 1-107)	Surface and mesh plots, view control, lighting and transparency, volume visualization

GUI Development (p. 1-113)	GUIDE, programming graphical user interfaces
External Interfaces (p. 1-118)	Interfaces to shared libraries, Java, .NET, COM and ActiveX, Web services, and serial port devices, and C and Fortran routines

Desktop Tools and Development Environment

Startup and Shutdown (p. 1-3)	Startup and shutdown options, preferences
Command Window and History (p. 1-4)	Control Command Window and History, enter statements and run functions
Help for Using MATLAB (p. 1-5)	Command line help, online documentation in the Help browser, demos
Workspace (p. 1-6)	Manage variables
Managing Files (p. 1-6)	Work with files, MATLAB search path, manage variables
Programming Tools (p. 1-8)	Edit and debug MATLAB code , improve performance, source control, publish results
System (p. 1-10)	Identify current computer, license, product version, and more

Startup and Shutdown

exit	Terminate MATLAB® program (same as quit)
finish	Termination M-file for MATLAB program
matlab (UNIX)	Start MATLAB program (UNIX® platforms)
matlab (Windows)	Start MATLAB program (Windows® platforms)
matlabrc	Startup M-file for MATLAB program
prefdir	Folder containing preferences, history, and layout files
preferences	Open Preferences dialog box

quit	Terminate MATLAB program
startup	Startup file for user-defined options
userpath	View or change user portion of search path

Command Window and History

clc	Clear Command Window
commandhistory	Open Command History window, or select it if already open
commandwindow	Open Command Window, or select it if already open
diary	Save session to file
dos	Execute DOS command and return result
format	Set display format for output
home	Send the cursor home
matlabcolon (matlab:)	Run specified function via hyperlink
more	Control paged output for Command Window
perl	Call Perl script using appropriate operating system executable
system	Execute operating system command and return result
unix	Execute UNIX command and return result

Help for Using MATLAB

builddocsearchdb	Build searchable documentation database
demo	Access product demos via Help browser
doc	Reference page in Help browser
docsearch	Help browser search
echodemo	Run scripted demo step-by-step in Command Window
help	Help for functions in Command Window
helpbrowser	Open Help browser to access online documentation and demos
helpwin	Provide access to help comments for all functions
info	Information about contacting The MathWorks
lookfor	Search for keyword in all help entries
playshow	Run M-file demo (deprecated; use echodemo instead)
support	Open MathWorks Technical Support Web page
web	Open Web site or file in Web or Help browser
whatsnew	Release Notes for MathWorks™ products

Workspace

clear	Remove items from workspace, freeing up system memory
delete	Remove files or graphics objects
openvar	Open workspace variable in Variable Editor or other graphical editing tool
pack	Consolidate workspace memory
which	Locate functions and files
who, whos	List variables in workspace
workspace	Open Workspace browser to manage workspace

Managing Files

Search Path (p. 1-6)	View and change MATLAB search path
File Operations (p. 1-7)	View and change files and directories

Search Path

addpath	Add folders to search path
genpath	Generate path string
path	View or change search path
path2rc	Save current search path to pathdef.m file
pathsep	Search path separator for current platform
pathtool	Open Set Path dialog box to view and change search path
restoredefaultpath	Restore default search path

rmpath	Remove folders from search path
savepath	Save current search path
userpath	View or change user portion of search path
which	Locate functions and files

File Operations

See also "Data Import and Export" on page 1-12 functions.

cd	Change current folder
copyfile	Copy file or folder
delete	Remove files or graphics objects
dir	Folder listing
fileattrib	Set or get attributes of file or folder
filebrowser	Open Current Folder browser, or select it if already open
isdir	Determine whether input is folder
lookfor	Search for keyword in all help entries
ls	Folder contents
matlabroot	Root folder
mkdir	Make new folder
movefile	Move file or folder
pwd	Identify current folder
recycle	Set option to move deleted files to recycle folder
rmdir	Remove folder
tempdir	Name of system's temporary folder
toolboxdir	Root folder for specified toolbox

type	Display contents of file
visdiff	Compare two text files, MAT-Files, binary files, or folders

Programming Tools

Editing Files (p. 1-8)	Edit files
Debugging Programs (p. 1-8)	Debug MATLAB program files
MATLAB Program Performance (p. 1-9)	Improve performance and find potential problems in MATLAB code
Source Control (p. 1-9)	Interface MATLAB with source control system
Publishing (p. 1-9)	Publish MATLAB code and results

Editing Files

 edit

Debugging Programs

dbclear	Clear breakpoints
dbcont	Resume execution
dbdown	Reverse workspace shift performed by dbup, while in debug mode
dbquit	Quit debug mode
dbstack	Function call stack
dbstatus	List all breakpoints
dbstep	Execute one or more lines from current breakpoint
dbstop	Set breakpoints

dbtype	List text file with line numbers
dbup	Shift current workspace to workspace of caller, while in debug mode

MATLAB Program Performance

rehash	Refresh function and file system
	path caches

Source Control

checkin	Check files into source control system (UNIX platforms)
checkout	Check files out of source control system (UNIX platforms)
cmopts	Name of source control system
customverctrl	Allow custom source control system (UNIX platforms)
undocheckout	Undo previous checkout from source control system (UNIX platforms)
verctrl	Source control actions (Windows platforms)
Publishing	
grabcode	MATLAB code from files published

grabcode	MATLAB code from files published to HTML
notebook	Open M-book in Microsoft® Word software (on Microsoft Windows platforms)

publish	Publish MATLAB file with code cells, saving output to specified file type
snapnow	Force snapshot of image for inclusion in published document

System

Operating System Interface (p. 1-10)	Exchange operating system information and commands with MATLAB
MATLAB Version and License (p. 1-11)	Information about MATLAB version and license

Operating System Interface

clipboard	Copy and paste strings to and from system clipboard
computer	Information about computer on which MATLAB software is running
dos	Execute DOS command and return result
getenv	Environment variable
hostid	Server host identification number
perl	Call Perl script using appropriate operating system executable
setenv	Set environment variable
system	Execute operating system command and return result
unix	Execute UNIX command and return result
winqueryreg	Item from Windows registry

MATLAB Version and License

ismac	Determine if version is for Mac OS® X platform
ispc	Determine if version is for Windows (PC) platform
isstudent	Determine if version is Student Version
isunix	Determine if version is for UNIX platform
javachk	Generate error message based on Sun™ Java™ feature support
license	Return license number or perform licensing task
prefdir	Folder containing preferences, history, and layout files
usejava	Determine whether Sun Java feature is supported in MATLAB software
ver	Version information for MathWorks products
verLessThan	Compare toolbox version to specified version string
version	Version number for MATLAB and libraries

Data Import and Export

et path, directory, filename nformation; construct filenames
pen files; transfer data between les and MATLAB workspace
ccess file data via memory map sing MATLAB array indexing
ow-level operations that use a file dentifier
Delimited or formatted I/O to text les
ocuments written in Extensible Iarkup Language
excel and Lotus 1-2-3 files
DF, FITS, HDF formats
ead and write audio and video, ecord and play audio
raphics files
URL, FTP, zip, tar, and e-mail

To see a listing of file formats that are readable from MATLAB, go to file formats.

File Name Construction

filemarker	Character to separate file name and internal function name
fileparts	Parts of file name and path
filesep	File separator for current platform
fullfile	Build full file name from parts

tempdir	Name of system's temporary folder
tempname	Unique name for temporary file

File Opening, Loading, and Saving

daqread	Read Data Acquisition Toolbox™ (.daq) file
importdata	Load data from file
load	Load data from MAT-file into workspace
open	Open file in appropriate application
save	Save workspace variables to file
uigetdir	Open standard dialog box for selecting directory
uigetfile	Open standard dialog box for retrieving files
uiimport	Open Import Wizard to import data
uiputfile	Open standard dialog box for saving files
uisave	Open standard dialog box for saving workspace variables
winopen	Open file in appropriate application (Windows)

Memory Mapping

disp (memmapfile)	Information about memmapfile object
get (memmapfile)	Memmapfile object properties
memmapfile	Construct memmapfile object

Low-Level File I/O

fclose	Close one or all open files
feof	Test for end-of-file
ferror	Information about file I/O errors
fgetl	Read line from file, removing newline characters
fgets	Read line from file, keeping newline characters
fopen	Open file, or obtain information about open files
fprintf	Write data to text file
fread	Read data from binary file
frewind	Move file position indicator to beginning of open file
fscanf	Read data from a text file
fseek	Move to specified position in file
ftell	Position in open file
fwrite	Write data to binary file

Text Files

csvread	Read comma-separated value file
csvwrite	Write comma-separated value file
dlmread	Read ASCII-delimited file of numeric data into matrix
dlmwrite	Write matrix to ASCII-delimited file
fileread	Read contents of file into string
textread	Read data from text file; write to multiple outputs

textscan	Read formatted data from text file or string
type	Display contents of file
XML Documents	

xmlread	Parse XML document and return Document Object Model node
xmlwrite	Serialize XML Document Object Model node
xslt	Transform XML document using XSLT engine

Spreadsheets

Microsoft Excel (p. 1-15)	Read and write Microsoft Excel spreadsheet
Lotus 1-2-3 (p. 1-16)	Read and write Lotus WK1 spreadsheet

Microsoft Excel

xlsfinfo	Determine whether file contains a Microsoft [®] Excel [®] spreadsheet
xlsread	Read Microsoft Excel spreadsheet file
xlswrite	Write Microsoft Excel spreadsheet file

Lotus 1-2-3

wk1finfo	Determine whether file contains 1-2-3 WK1 worksheet
wk1read	Read Lotus 1-2-3 WK1 spreadsheet file into matrix
wk1write	Write matrix to Lotus 1-2-3 WK1 spreadsheet file

Scientific Data

Common Data Format (p. 1-16)	Work with CDF files
Network Common Data Form (p. 1-22)	Work with netCDF files
Flexible Image Transport System (p. 1-23)	Work with FITS files
Hierarchical Data Format (p. 1-24)	Work with HDF files
Band-Interleaved Data (p. 1-24)	Work with band-interleaved files

Common Data Format

High-level I/O Functions

cdfepoch	Convert MATLAB formatted dates to CDF formatted dates
cdfinfo	Information about Common Data Format (CDF) file
cdfread	Read data from Common Data Format (CDF) file
cdfwrite	Write data to Common Data Format (CDF) file
todatenum	Convert CDF epoch object to MATLAB datenum

Library Information

cdflib	Summary of Common Data Format (CDF) capabilities
cdflib.getConstantNames	Names of Common Data Format (CDF) library constants
cdflib.getConstantValue	Numeric value corresponding to Common Data Format (CDF) library constant
cdflib.getLibraryCopyright	Copyright notice of Common Data Format (CDF) library
cdflib.getLibraryVersion	Library version and release information
cdflib.getValidate	Library validation mode
cdflib.setValidate	Specify library validation mode
File Operations	
cdflib.close	Close Common Data Format (CDF) file
cdflib.create	Create Common Data Format (CDF) file
cdflib.delete	Delete existing Common Data Format (CDF) file
cdflib.getCacheSize	Number of cache buffers used
cdflib.getChecksum	Checksum mode
cdflib.getCompression	Compression settings

cdflib.getCompressionCacheSize

cdflib.getCopyright

cdflib.getFormat

Number of compression cache buffers

Copyright notice in Common Data Format (CDF) file

Format of Common Data Format (CDF) file

cdflib.getMajority	Majority of variables
cdflib.getName	Name of Common Data Format (CDF) file
cdflib.getReadOnlyMode	Read-only mode
cdflib.getStageCacheSize	Number of cache buffers for staging
cdflib.getVersion	Common Data Format (CDF) library version and release information
cdflib.inquire	Basic characteristics of Common Data Format (CDF) file
cdflib.open	Open existing Common Data Format (CDF) file
cdflib.setCacheSize	Specify number of dotCDF cache buffers
cdflib.setChecksum	Specify checksum mode
cdflib.setCompression	Specify compression settings
cdflib.setCompressionCacheSize	Specify number of compression cache buffers
cdflib.setFormat	Specify format of Common Data Format (CDF) file
cdflib.setMajority	Specify majority of variables
cdflib.setReadOnlyMode	Specify read-only mode
cdflib.setStageCacheSize	Specify number of staging cache buffers for Common Data Format (CDF) file
Variables	
cdflib.closeVar	Close specified variable from multifile format Common Data Format (CDF) file
cdflib.createVar	Create new variable

Delete variable

cdflib.deleteVar

cdflib.deleteVarRecords	Delete range of records from variable
cdflib.getVarAllocRecords	Number of records allocated for variable
cdflib.getVarBlockingFactor	Blocking factor for variable
cdflib.getVarCacheSize	Number of multifile cache buffers
cdflib.getVarCompression	Information about compression used by variable
cdflib.getVarData	Single value from record in variable
cdflib.getVarMaxAllocRecNum	Maximum allocated record number for variable
cdflib.getVarMaxWrittenRecNum	Maximum written record number for variable
cdflib.getVarName	Variable name, given variable number
cdflib.getVarNum	Variable number, given variable name
cdflib.getVarNumRecsWritten	Number of records written to variable
cdflib.getVarPadValue	Pad value for variable
cdflib.getVarRecordData	Entire record for variable
cdflib.getVarReservePercent	Compression reserve percentage for variable
cdflib.getVarSparseRecords	Information about how variable handles sparse records
cdflib.hyperGetVarData	Read hyperslab of data from variable
cdflib.hyperPutVarData	Write hyperslab of data to variable
cdflib.inquireVar	Information about variable
cdflib.putVarData	Write single value to variable
cdflib.putVarRecordData	Write entire record to variable
cdflib.renameVar	Rename existing variable

cdflib.setVarAllocBlockRecords	Specify range of records to be allocated for variable
cdflib.setVarBlockingFactor	Specify blocking factor for variable
cdflib.setVarCacheSize	Specify number of multi-file cache buffers for variable
cdflib.setVarCompression	Specify compression settings used with variable
cdflib.setVarInitialRecs	Specify initial number of records written to variable
cdflib.setVarPadValue	Specify pad value used with variable
cdflib.SetVarReservePercent	Specify reserve percentage for variable
cdflib.setVarsCacheSize	Specify number of cache buffers used for all variables
cdflib.setVarSparseRecords	Specify how variable handles sparse records

Attributes and Entries

cdflib.createAttr	Create attribute
cdflib.deleteAttr	Delete attribute
cdflib.deleteAttrEntry	Delete attribute entry
cdflib.deleteAttrgEntry	Delete entry in global attribute
cdflib.getAttrEntry	Value of entry in attribute with variable scope
cdflib.getAttrgEntry	Value of entry in global attribute
cdflib.getAttrMaxEntry	Number of last entry for variable attribute
cdflib.getAttrMaxgEntry	Number of last entry for global attribute
cdflib.getAttrName	Name of attribute, given attribute number

cdflib.getAttrNum	Attribute number, given attribute name
cdflib.getAttrScope	Scope of attribute
cdflib.getNumAttrEntries	Number of entries for attribute with variable scope
cdflib.getNumAttrgEntries	Number of entries for attribute with global scope
cdflib.getNumAttributes	Number of attributes with variable scope
cdflib.getNumgAttributes	Number of attributes with global scope
cdflib.inquireAttr	Information about attribute
cdflib.inquireAttrEntry	Information about entry in attribute with variable scope
cdflib.inquireAttrgEntry	Information about entry in attribute with global scope
cdflib.putAttrEntry	Write value to entry in attribute with variable scope
cdflib.putAttrgEntry	Write value to entry in attribute with global scope
cdflib.renameAttr	Rename existing attribute
Utilities	
cdflib.computeEpoch	Convert time value to CDF_EPOCH value
cdflib.computeEpoch16	Convert time value to CDF_EPOCH16 value
cdflib.epoch16Breakdown	Convert CDF_EPOCH16 value to time value
cdflib.epochBreakdown	Convert CDF_EPOCH value into time value

Network Common Data Form File Operations

netcdf	Summary of MATLAB Network Common Data Form (netCDF) capabilities
netcdf.abort	Revert recent netCDF file definitions
netcdf.close	Close netCDF file
netcdf.create	Create new netCDF dataset
netcdf.endDef	End netCDF file define mode
netcdf.getConstant	Return numeric value of named constant
netcdf.getConstantNames	Return list of constants known to netCDF library
netcdf.inq	Return information about netCDF file
netcdf.inqLibVers	Return netCDF library version information
netcdf.open	Open netCDF file
netcdf.reDef	Put open netCDF file into define mode
netcdf.setDefaultFormat	Change default netCDF file format
netcdf.setFill	Set netCDF fill mode
netcdf.sync	Synchronize netCDF file to disk
Dimensions	
netcdf.defDim	Create netCDF dimension
netcdf.inqDim	Return netCDF dimension name and length
netcdf.inqDimID	Return dimension ID
netcdf.renameDim	Change name of netCDF dimension

Variables

netcdf.defVar	Create netCDF variable
netcdf.getVar	Return data from $netCDF$ variable
netcdf.inqVar	Return information about variable
netcdf.inqVarID	Return ID associated with variable name
netcdf.putVar	Write data to netCDF variable
netcdf.renameVar	Change name of netCDF variable

Attributes

netcdf.copyAtt	Copy attribute to new location
netcdf.delAtt	Delete netCDF attribute
netcdf.getAtt	Return netCDF attribute
netcdf.inqAtt	Return information about netCDF attribute
netcdf.inqAttID	Return ID of netCDF attribute
netcdf.inqAttName	Return name of netCDF attribute
netcdf.putAtt	Write netCDF attribute
netcdf.renameAtt	Change name of attribute

Flexible Image Transport System

fitsinfo	Information about FITS file
fitsread	Read data from FITS file

Hierarchical Data Format

hdf	Summary of MATLAB HDF4 capabilities
hdf5	Summary of MATLAB HDF5 capabilities
hdf5info	Information about HDF5 file
hdf5read	Read HDF5 file
hdf5write	Write data to file in HDF5 format
hdfinfo	Information about HDF4 or HDF-EOS file
hdfread	Read data from HDF4 or HDF-EOS file
hdftool	Browse and import data from HDF4 or HDF-EOS files

Band-Interleaved Data

multibandread	Read band-interleaved data from binary file
multibandwrite	Write band-interleaved data to file

Audio and Video

Reading and Writing Files (p. 1-25)	Input/output data to audio and video file formats
Recording and Playback (p. 1-25)	Record and listen to audio
Utilities (p. 1-26)	Convert audio signal

Reading and Writing Files

aufinfo	Information about NeXT/SUN (.au) sound file
auread	Read NeXT/SUN (.au) sound file
auwrite	Write NeXT/SUN (.au) sound file
avifile	Create new Audio/Video Interleaved (AVI) file
aviinfo	Information about Audio/Video Interleaved (AVI) file
aviread	Read Audio/Video Interleaved (AVI) file
mmfileinfo	Information about multimedia file
mmreader	Create multimedia reader object for reading video files
movie2avi	Create Audio/Video Interleaved (AVI) file from MATLAB movie
wavfinfo	Information about WAVE (.wav) sound file
wavread	Read WAVE (.wav) sound file
wavwrite	Write WAVE (.wav) sound file

Recording and Playback

audiodevinfo	Information about audio device
audioplayer	Create object for playing audio
audiorecorder	Create object for recording audio
sound	Convert matrix of signal data to sound
soundsc	Scale data and play as sound

wavplay	Play recorded sound on PC-based audio output device
wavrecord	Record sound using PC-based audio input device
Utilities	

beep	Produce beep sound
lin2mu	Convert linear audio signal to mu-law
mu2lin	Convert mu-law audio signal to linear

Images

exifread	Read EXIF information from JPEG and TIFF image files
im2java	Convert image to Java image
imfinfo	Information about graphics file
imread	Read image from graphics file
imwrite	Write image to graphics file
Tiff	MATLAB Gateway to LibTIFF library routines

Internet Exchange

URL, Zip, Tar, E-Mail (p. 1-27)	Send e-mail, read from given URL, extract from tar or zip file, compress and decompress files
FTP (p. 1-27)	Connect to FTP server, download from server, manage FTP files, close server connection

URL, Zip, Tar, E-Mail

gunzip	Uncompress GNU zip files
gzip	Compress files into GNU zip files
sendmail	Send e-mail message to address list
tar	Compress files into tar file
untar	Extract contents of tar file
unzip	Extract contents of zip file
urlread	Download content at URL into MATLAB string
urlwrite	Download content at URL and save to file
zip	Compress files into zip file

FTP

ascii	Set FTP transfer type to ASCII
binary	Set FTP transfer type to binary
cd (ftp)	Change current directory on FTP server
close (ftp)	Close connection to FTP server
delete (ftp)	Remove file on FTP server
dir (ftp)	Directory contents on FTP server
ftp	Connect to FTP server, creating FTP object
mget	Download file from FTP server
mkdir (ftp)	Create new directory on FTP server
mput	Upload file or directory to FTP server
rename	Rename file on FTP server
rmdir (ftp)	Remove directory on FTP server

Mathematics

Arrays and Matrices (p. 1-29)	Basic array operators and operations, creation of elementary and specialized arrays and matrices
Linear Algebra (p. 1-34)	Matrix analysis, linear equations, eigenvalues, singular values, logarithms, exponentials, factorization
Elementary Math (p. 1-38)	Trigonometry, exponentials and logarithms, complex values, rounding, remainders, discrete math
Polynomials (p. 1-43)	Multiplication, division, evaluation, roots, derivatives, integration, eigenvalue problem, curve fitting, partial fraction expansion
Interpolation and Computational Geometry (p. 1-43)	Interpolation, Delaunay triangulation and tessellation, convex hulls, Voronoi diagrams, domain generation
Cartesian Coordinate System Conversion (p. 1-47)	Conversions between Cartesian and polar or spherical coordinates
Nonlinear Numerical Methods (p. 1-47)	Differential equations, optimization, integration
Specialized Math (p. 1-51)	Airy, Bessel, Jacobi, Legendre, beta, elliptic, error, exponential integral, gamma functions
Sparse Matrices (p. 1-52)	Elementary sparse matrices, operations, reordering algorithms, linear algebra, iterative methods, tree operations
Math Constants (p. 1-55)	Pi, imaginary unit, infinity, Not-a-Number, largest and smallest positive floating point numbers, floating point relative accuracy

Arrays and Matrices

Basic Information (p. 1-29)	Display array contents, get array information, determine array type
Operators (p. 1-30)	Arithmetic operators
Elementary Matrices and Arrays (p. 1-31)	Create elementary arrays of different types, generate arrays for plotting, array indexing, etc.
Array Operations (p. 1-32)	Operate on array content, apply function to each array element, find cumulative product or sum, etc.
Array Manipulation (p. 1-33)	Create, sort, rotate, permute, reshape, and shift array contents
Specialized Matrices (p. 1-34)	Create Hadamard, Companion, Hankel, Vandermonde, Pascal matrices, etc.

Basic Information

disp	Display text or array
display	Display text or array (overloaded method)
isempty	Determine whether array is empty
isequal	Test arrays for equality
isequalwithequalnans	Test arrays for equality, treating NaNs as equal
isfinite	Array elements that are finite
isfloat	Determine whether input is floating-point array
isinf	Array elements that are infinite
isinteger	Determine whether input is integer array

islogical	Determine whether input is logical array
isnan	Array elements that are NaN
isnumeric	Determine whether input is numeric array
isscalar	Determine whether input is scalar
issparse	Determine whether input is sparse
isvector	Determine whether input is vector
length	Length of vector or largest array dimension
max	Largest elements in array
min	Smallest elements in array
ndims	Number of array dimensions
numel	Number of elements in array or subscripted array expression
size	Array dimensions

Operators

+	Addition
+	Unary plus
-	Subtraction
-	Unary minus
*	Matrix multiplication
٨	Matrix power
\backslash	Backslash or left matrix divide
1	Slash or right matrix divide
,	Transpose
; ·	Nonconjugated transpose

- .* Array multiplication (element-wise)
- .^ Array power (element-wise)
- .\ Left array divide (element-wise)
- ./ Right array divide (element-wise)

Elementary Matrices and Arrays

blkdiag	Construct block diagonal matrix from input arguments
diag	Diagonal matrices and diagonals of matrix
eye	Identity matrix
freqspace	Frequency spacing for frequency response
ind2sub	Subscripts from linear index
linspace	Generate linearly spaced vectors
logspace	Generate logarithmically spaced vectors
meshgrid	Generate X and Y arrays for 3-D plots
ndgrid	Generate arrays for N-D functions and interpolation
ones	Create array of all ones
rand	Uniformly distributed pseudorandom numbers
randi	Uniformly distributed pseudorandom integers
randn	Normally distributed pseudorandom numbers
RandStream	Random number stream

sub2ind	Convert subscripts to linear indices
zeros	Create array of all zeros

Array Operations

See "Linear Algebra" on page 1-34 and "Elementary Math" on page 1-38 for other array operations.

accumarray	Construct array with accumulation
arrayfun	Apply function to each element of array
bsxfun	Apply element-by-element binary operation to two arrays with singleton expansion enabled
cast	Cast variable to different data type
cross	Vector cross product
cumprod	Cumulative product
cumsum	Cumulative sum
dot	Vector dot product
idivide	Integer division with rounding option
kron	Kronecker tensor product
prod	Product of array elements
sum	Sum of array elements
tril	Lower triangular part of matrix
triu	Upper triangular part of matrix

Array Manipulation

blkdiag	Construct block diagonal matrix from input arguments
cat	Concatenate arrays along specified dimension
circshift	Shift array circularly
diag	Diagonal matrices and diagonals of matrix
end	Terminate block of code, or indicate last array index
flipdim	Flip array along specified dimension
fliplr	Flip matrix left to right
flipud	Flip matrix up to down
horzcat	Concatenate arrays horizontally
inline	Construct inline object
ipermute	Inverse permute dimensions of N-D array
permute	Rearrange dimensions of N-D array
repmat	Replicate and tile array
reshape	Reshape array
rot90	Rotate matrix 90 degrees
shiftdim	Shift dimensions
sort	Sort array elements in ascending or descending order
sortrows	Sort rows in ascending order
squeeze	Remove singleton dimensions
vectorize	Vectorize expression
vertcat	Concatenate arrays vertically

Specialized Matrices

compan	Companion matrix
gallery	Test matrices
hadamard	Hadamard matrix
hankel	Hankel matrix
hilb	Hilbert matrix
invhilb	Inverse of Hilbert matrix
magic	Magic square
pascal	Pascal matrix
rosser	Classic symmetric eigenvalue test problem
toeplitz	Toeplitz matrix
vander	Vandermonde matrix
wilkinson	Wilkinson's eigenvalue test matrix

Linear Algebra

Matrix Analysis (p. 1-35)	Compute norm, rank, determinant, condition number, etc.
Linear Equations (p. 1-35)	Solve linear systems, least squares, LU factorization, Cholesky factorization, etc.
Eigenvalues and Singular Values (p. 1-36)	Eigenvalues, eigenvectors, Schur decomposition, Hessenburg matrices, etc.
Matrix Logarithms and Exponentials (p. 1-37)	Matrix logarithms, exponentials, square root
Factorization (p. 1-37)	Cholesky, LU, and QR factorizations, diagonal forms, singular value decomposition

Matrix Analysis

cond	Condition number with respect to inversion
condeig	Condition number with respect to eigenvalues
det	Matrix determinant
norm	Vector and matrix norms
normest	2-norm estimate
null	Null space
orth	Range space of matrix
rank	Rank of matrix
rcond	Matrix reciprocal condition number estimate
rref	Reduced row echelon form
subspace	Angle between two subspaces
trace	Sum of diagonal elements

Linear Equations

chol	Cholesky factorization
cholinc	Sparse incomplete Cholesky and Cholesky-Infinity factorizations
cond	Condition number with respect to inversion
condest	1-norm condition number estimate
funm	Evaluate general matrix function
ilu	Sparse incomplete LU factorization
inv	Matrix inverse

ldl	Block LDL' factorization for Hermitian indefinite matrices
linsolve	Solve linear system of equations
lscov	Least-squares solution in presence of known covariance
lsqnonneg	Solve nonnegative least-squares constraints problem
lu	LU matrix factorization
luinc	Sparse incomplete LU factorization
pinv	Moore-Penrose pseudoinverse of matrix
\mathbf{qr}	Orthogonal-triangular decomposition
rcond	Matrix reciprocal condition number estimate

Eigenvalues and Singular Values

balance	Diagonal scaling to improve eigenvalue accuracy
cdf2rdf	Convert complex diagonal form to real block diagonal form
condeig	Condition number with respect to eigenvalues
eig	Eigenvalues and eigenvectors
eigs	Largest eigenvalues and eigenvectors of matrix
gsvd	Generalized singular value decomposition
hess	Hessenberg form of matrix
ordeig	Eigenvalues of quasitriangular matrices

ordqz	Reorder eigenvalues in QZ factorization
ordschur	Reorder eigenvalues in Schur factorization
poly	Polynomial with specified roots
polyeig	Polynomial eigenvalue problem
rsf2csf	Convert real Schur form to complex Schur form
schur	Schur decomposition
sqrtm	Matrix square root
ss2tf	Convert state-space filter parameters to transfer function form
svd	Singular value decomposition
svds	Find singular values and vectors

Matrix Logarithms and Exponentials

expm	Matrix exponential
logm	Matrix logarithm
sqrtm	Matrix square root

Factorization

balance	Diagonal scaling to improve eigenvalue accuracy
cdf2rdf	Convert complex diagonal form to real block diagonal form
chol	Cholesky factorization
cholinc	Sparse incomplete Cholesky and Cholesky-Infinity factorizations

cholupdate	Rank 1 update to Cholesky factorization
gsvd	Generalized singular value decomposition
ilu	Sparse incomplete LU factorization
ldl	Block LDL' factorization for Hermitian indefinite matrices
lu	LU matrix factorization
luinc	Sparse incomplete LU factorization
planerot	Givens plane rotation
qr	Orthogonal-triangular decomposition
qrdelete	Remove column or row from QR factorization
qrinsert	Insert column or row into QR factorization
qrupdate	
qz	QZ factorization for generalized eigenvalues
rsf2csf	Convert real Schur form to complex Schur form
svd	Singular value decomposition

Elementary Math

Trigonometric (p. 1-39)	Trigonometric functions with results in radians or degrees
Exponential (p. 1-40)	Exponential, logarithm, power, and root functions
Complex (p. 1-41)	Numbers with real and imaginary components, phase angles

Rounding and Remainder (p. 1-42)	Rounding, modulus, and remainder
Discrete Math (p. 1-42)	Prime factors, factorials, permutations, rational fractions, least common multiple, greatest common divisor

Trigonometric

acos	Inverse cosine; result in radians
acosd	Inverse cosine; result in degrees
acosh	Inverse hyperbolic cosine
acot	Inverse cotangent; result in radians
acotd	Inverse cotangent; result in degrees
acoth	Inverse hyperbolic cotangent
acsc	Inverse cosecant; result in radians
acscd	Inverse cosecant; result in degrees
acsch	Inverse hyperbolic cosecant
asec	Inverse secant; result in radians
asecd	Inverse secant; result in degrees
asech	Inverse hyperbolic secant
asin	Inverse sine; result in radians
asind	Inverse sine; result in degrees
asinh	Inverse hyperbolic sine
atan	Inverse tangent; result in radians
atan2	Four-quadrant inverse tangent
atand	Inverse tangent; result in degrees
atanh	Inverse hyperbolic tangent
cos	Cosine of argument in radians
cosd	Cosine of argument in degrees

cosh	Hyperbolic cosine
\cot	Cotangent of argument in radians
cotd	Cotangent of argument in degrees
coth	Hyperbolic cotangent
csc	Cosecant of argument in radians
cscd	Cosecant of argument in degrees
csch	Hyperbolic cosecant
hypot	Square root of sum of squares
sec	Secant of argument in radians
secd	Secant of argument in degrees
sech	Hyperbolic secant
sin	Sine of argument in radians
sind	Sine of argument in degrees
sinh	Hyperbolic sine of argument in radians
tan	Tangent of argument in radians
tand	Tangent of argument in degrees
tanh	Hyperbolic tangent

Exponential

exp	Exponential
expm1	Compute exp(x)-1 accurately for small values of x
log	Natural logarithm
log10	Common (base 10) logarithm
log1p	Compute log(1+x) accurately for small values of x

log2	Base 2 logarithm and dissect floating-point numbers into exponent and mantissa
nextpow2	Next higher power of 2
nthroot	Real nth root of real numbers
pow2	Base 2 power and scale floating-point numbers
reallog	Natural logarithm for nonnegative real arrays
realpow	Array power for real-only output
realsqrt	Square root for nonnegative real arrays
sqrt	Square root

Complex

abs	Absolute value and complex magnitude
angle	Phase angle
complex	Construct complex data from real and imaginary components
conj	Complex conjugate
cplxpair	Sort complex numbers into complex conjugate pairs
i	Imaginary unit
imag	Imaginary part of complex number
isreal	Check if input is real array
j	Imaginary unit
real	Real part of complex number

sign	Signum function
unwrap	Correct phase angles to produce smoother phase plots

Rounding and Remainder

ceil	Round toward positive infinity
fix	Round toward zero
floor	Round toward negative infinity
idivide	Integer division with rounding option
mod	Modulus after division
rem	Remainder after division
round	Round to nearest integer

Discrete Math

factor	Prime factors
factorial	Factorial function
gcd	Greatest common divisor
isprime	Array elements that are prime numbers
lcm	Least common multiple
nchoosek	Binomial coefficient or all combinations
perms	All possible permutations
primes	Generate list of prime numbers
rat, rats	Rational fraction approximation

Polynomials

conv	Convolution and polynomial multiplication
deconv	Deconvolution and polynomial division
poly	Polynomial with specified roots
polyder	Polynomial derivative
polyeig	Polynomial eigenvalue problem
polyfit	Polynomial curve fitting
polyint	Integrate polynomial analytically
polyval	Polynomial evaluation
polyvalm	Matrix polynomial evaluation
residue	Convert between partial fraction expansion and polynomial coefficients
roots	Polynomial roots

Interpolation and Computational Geometry

Interpolation (p. 1-44)	Data interpolation, data gridding, polynomial evaluation, nearest point search
Delaunay Triangulation and Tessellation (p. 1-45)	Delaunay triangulation and tessellation, triangular surface and mesh plots
Convex Hull (p. 1-46)	Plot convex hull, plotting functions
Voronoi Diagrams (p. 1-46)	Plot Voronoi diagram, patch graphics object, plotting functions
Domain Generation (p. 1-47)	Generate arrays for 3-D plots, or for N-D functions and interpolation

Interpolation

dsearch	Search Delaunay triangulation for nearest point
dsearchn	N-D nearest point search
griddata	Data gridding
griddata3	Data gridding and hypersurface fitting for 3-D data
griddatan	Data gridding and hypersurface fitting (dimension >= 2)
interp1	1-D data interpolation (table lookup)
interp1q	Quick 1-D linear interpolation
interp2	2-D data interpolation (table lookup)
interp3	3-D data interpolation (table lookup)
interpft	1-D interpolation using FFT method
interpn	N-D data interpolation (table lookup)
meshgrid	Generate X and Y arrays for 3-D plots
mkpp	Make piecewise polynomial
ndgrid	Generate arrays for N-D functions and interpolation
padecoef	Padé approximation of time delays
pchip	Piecewise Cubic Hermite Interpolating Polynomial (PCHIP)
ppval	Evaluate piecewise polynomial
spline	Cubic spline data interpolation
TriScatteredInterp	Interpolate scattered data
TriScatteredInterp	Interpolate scattered data
tsearch	Search for enclosing Delaunay triangle

tsearchn	N-D closest simplex search
unmkpp	Piecewise polynomial details

Delaunay Triangulation and Tessellation

baryToCart (TriRep)	Converts point coordinates from barycentric to Cartesian
cartToBary (TriRep)	Convert point coordinates from cartesian to barycentric
circumcenters (TriRep)	Circumcenters of specified simplices
delaunay	Delaunay triangulation
delaunay3	3-D Delaunay tessellation
delaunayn	N-D Delaunay tessellation
DelaunayTri	Contruct Delaunay triangulation
DelaunayTri	Delaunay triangulation in 2-D and 3-D
edgeAttachments (TriRep)	Simplices attached to specified edges
edges (TriRep)	Triangulation edges
faceNormals (TriRep)	Unit normals to specified triangles
featureEdges (TriRep)	Sharp edges of surface triangulation
freeBoundary (TriRep)	Facets referenced by only one simplex
incenters (TriRep)	Incenters of specified simplices
inOutStatus (DelaunayTri)	Status of triangles in 2-D constrained Delaunay triangulation
isEdge (TriRep)	Test if vertices are joined by edge
nearestNeighbor (DelaunayTri)	Point closest to specified location
neighbors (TriRep)	Simplex neighbor information
pointLocation (DelaunayTri)	Simplex containing specified location

size (TriRep)	Size of triangulation matrix
tetramesh	Tetrahedron mesh plot
trimesh	Triangular mesh plot
triplot	2-D triangular plot
TriRep	Triangulation representation
TriRep	Triangulation representation
trisurf	Triangular surface plot
vertexAttachments (TriRep)	Return simplices attached to specified vertices

Convex Hull

convexHull (DelaunayTri)	Convex hull
convhull	Convex hull
convhulln	N-D convex hull
patch	Create one or more filled polygons
trisurf	Triangular surface plot

Voronoi Diagrams

patch	Create one or more filled polygons
voronoi	Voronoi diagram
voronoiDiagram (DelaunayTri)	Voronoi diagram
voronoin	N-D Voronoi diagram

Domain Generation

meshgrid ndgrid Generate X and Y arrays for 3-D plots

Generate arrays for N-D functions and interpolation

Cartesian Coordinate System Conversion

cart2pol	Transform Cartesian coordinates to polar or cylindrical
cart2sph	Transform Cartesian coordinates to spherical
pol2cart	Transform polar or cylindrical coordinates to Cartesian
sph2cart	Transform spherical coordinates to Cartesian

Nonlinear Numerical Methods

Ordinary Differential Equations (p. 1-48)	Solve stiff and nonstiff differential equations, define the problem, set solver options, evaluate solution
Delay Differential Equations (p. 1-49)	Solve delay differential equations with constant and general delays, set solver options, evaluate solution
Boundary Value Problems (p. 1-49)	Solve boundary value problems for ordinary differential equations, set solver options, evaluate solution
Partial Differential Equations (p. 1-50)	Solve initial-boundary value problems for parabolic-elliptic PDEs, evaluate solution

Optimization (p. 1-50)	Find minimum of single and multivariable functions, solve nonnegative least-squares constraint problem
Numerical Integration (Quadrature) (p. 1-50)	Evaluate Simpson, Lobatto, and vectorized quadratures, evaluate double and triple integrals

Ordinary Differential Equations

decic	Compute consistent initial conditions for ode15i
deval	Evaluate solution of differential equation problem
ode15i	Solve fully implicit differential equations, variable order method
ode23, ode45, ode113, ode15s, ode23s, ode23t, ode23tb	Solve initial value problems for ordinary differential equations
odefile	Define differential equation problem for ordinary differential equation solvers
odeget	Ordinary differential equation options parameters
odeset	Create or alter options structure for ordinary differential equation solvers
odextend	Extend solution of initial value problem for ordinary differential equation

Delay Differential Equations

dde23	Solve delay differential equations (DDEs) with constant delays
ddeget	Extract properties from delay differential equations options structure
ddesd	Solve delay differential equations (DDEs) with general delays
ddeset	Create or alter delay differential equations options structure
deval	Evaluate solution of differential equation problem

Boundary Value Problems

bvp4c	Solve boundary value problems for ordinary differential equations
bvp5c	Solve boundary value problems for ordinary differential equations
bvpget	Extract properties from options structure created with bvpset
bvpinit	Form initial guess for bvp4c
bvpset	Create or alter options structure of boundary value problem
bvpxtend	Form guess structure for extending boundary value solutions
deval	Evaluate solution of differential equation problem

Partial Differential Equations

pdepe	Solve initial-boundary value problems for parabolic-elliptic PDEs in 1-D
pdeval	Evaluate numerical solution of PDE using output of pdepe
Optimization	
fminbnd	Find minimum of single-variable function on fixed interval
fminsearch	Find minimum of unconstrained multivariable function using derivative-free method
fzero	Find root of continuous function of one variable
lsqnonneg	Solve nonnegative least-squares constraints problem
optimget	Optimization options values
optimset	Create or edit optimization options structure

Numerical Integration (Quadrature)

dblquad	Numerically evaluate double integral over rectangle
quad	Numerically evaluate integral, adaptive Simpson quadrature
quad2d	Numerically evaluate double integral over planar region
quadgk	Numerically evaluate integral, adaptive Gauss-Kronrod quadrature

quadl	Numerically evaluate integral, adaptive Lobatto quadrature
quadv	Vectorized quadrature
triplequad	Numerically evaluate triple integral

Specialized Math

airy	Airy functions
besselh	Bessel function of third kind (Hankel function)
besseli	Modified Bessel function of first kind
besselj	Bessel function of first kind
besselk	Modified Bessel function of second kind
bessely	Bessel function of second kind
beta	Beta function
betainc	Incomplete beta function
betaincinv	Beta inverse cumulative distribution function
betaln	Logarithm of beta function
ellipj	Jacobi elliptic functions
ellipke	Complete elliptic integrals of first and second kind
erf, erfc, erfcx, erfinv, erfcinv	Error functions
expint	Exponential integral
gamma, gammainc, gammaln	Gamma functions
gammaincinv	Inverse incomplete gamma function
legendre	Associated Legendre functions
psi	Psi (polygamma) function

Sparse Matrices

Elementary Sparse Matrices (p. 1-52)	Create random and nonrandom sparse matrices
Full to Sparse Conversion (p. 1-53)	Convert full matrix to sparse, sparse matrix to full
Sparse Matrix Manipulation (p. 1-53)	Test matrix for sparseness, get information on sparse matrix, allocate sparse matrix, apply function to nonzero elements, visualize sparsity pattern
Reordering Algorithms (p. 1-53)	Random, column, minimum degree, Dulmage-Mendelsohn, and reverse Cuthill-McKee permutations
Linear Algebra (p. 1-54)	Compute norms, eigenvalues, factorizations, least squares, structural rank
Linear Equations (Iterative Methods) (p. 1-54)	Methods for conjugate and biconjugate gradients, residuals, lower quartile
Tree Operations (p. 1-55)	Elimination trees, tree plotting, factorization analysis

Elementary Sparse Matrices

spdiags	Extract and create sparse band and diagonal matrices
speye	Sparse identity matrix
sprand	Sparse uniformly distributed random matrix
sprandn	Sparse normally distributed random matrix
sprandsym	Sparse symmetric random matrix

Full to Sparse Conversion

find	Find indices and values of nonzero elements
full	Convert sparse matrix to full matrix
sparse	Create sparse matrix
spconvert	Import matrix from sparse matrix external format

Sparse Matrix Manipulation

issparse	Determine whether input is sparse
nnz	Number of nonzero matrix elements
nonzeros	Nonzero matrix elements
nzmax	Amount of storage allocated for nonzero matrix elements
spalloc	Allocate space for sparse matrix
spfun	Apply function to nonzero sparse matrix elements
spones	Replace nonzero sparse matrix elements with ones
spparms	Set parameters for sparse matrix routines
spy	Visualize sparsity pattern

Reordering Algorithms

amd	Approximate minimum degree permutation
colamd	Column approximate minimum degree permutation

colperm	Sparse column permutation based on nonzero count
dmperm	Dulmage-Mendelsohn decomposition
ldl	Block LDL' factorization for Hermitian indefinite matrices
randperm	Random permutation
symamd	Symmetric approximate minimum degree permutation
symrcm	Sparse reverse Cuthill-McKee ordering

Linear Algebra

cholinc	Sparse incomplete Cholesky and Cholesky-Infinity factorizations
condest	1-norm condition number estimate
eigs	Largest eigenvalues and eigenvectors of matrix
ilu	Sparse incomplete LU factorization
luinc	Sparse incomplete LU factorization
normest	2-norm estimate
spaugment	Form least squares augmented system
sprank	Structural rank
svds	Find singular values and vectors

Linear Equations (Iterative Methods)

bicg	Biconjugate gradients method
bicgstab	Biconjugate gradients stabilized method

bicgstabl	Biconjugate gradients stabilized (l) method
cgs	Conjugate gradients squared method
gmres	Generalized minimum residual method (with restarts)
lsqr	LSQR method
minres	Minimum residual method
pcg	Preconditioned conjugate gradients method
qmr	Quasi-minimal residual method
symmlq	Symmetric LQ method
tfqmr	Transpose-free quasi-minimal residual method

Tree Operations

etree	Elimination tree
etreeplot	Plot elimination tree
gplot	Plot nodes and links representing adjacency matrix
symbfact	Symbolic factorization analysis
treelayout	Lay out tree or forest
treeplot	Plot picture of tree
unmesh	Convert edge matrix to coordinate and Laplacian matrices

Math Constants

eps
i

Floating-point relative accuracy Imaginary unit

Inf	Infinity
intmax	Largest value of specified integer type
intmin	Smallest value of specified integer type
j	Imaginary unit
NaN	Not-a-Number
pi	Ratio of circle's circumference to its diameter
realmax	Largest positive floating-point number
realmin	Smallest positive normalized floating-point number

Data Analysis

Basic Operations (p. 1-57)	Sums, products, sorting
Descriptive Statistics (p. 1-57)	Statistical summaries of data
Filtering and Convolution (p. 1-58)	Data preprocessing
Interpolation and Regression (p. 1-58)	Data fitting
Fourier Transforms (p. 1-59)	Frequency content of data
Derivatives and Integrals (p. 1-59)	Data rates and accumulations
Time Series Objects (p. 1-60)	Methods for timeseries objects
Time Series Collections (p. 1-63)	Methods for tscollection objects

Basic Operations

Interactively mark, delete, modify, and save observations in graphs
Cumulative product
Cumulative sum
Automatically update graphs when variables change
Product of array elements
Sort array elements in ascending or descending order
Sort rows in ascending order
Sum of array elements

Descriptive Statistics

corrcoef	Correlation coefficients
cov	Covariance matrix

max	Largest elements in array
mean	Average or mean value of array
median	Median value of array
min	Smallest elements in array
mode	Most frequent values in array
std	Standard deviation
var	Variance

Filtering and Convolution

conv	Convolution and polynomial multiplication
conv2	2-D convolution
convn	N-D convolution
deconv	Deconvolution and polynomial division
detrend	Remove linear trends
filter	1-D digital filter
filter2	2-D digital filter

Interpolation and Regression

interp1	1-D data interpolation (table lookup)
interp2	2-D data interpolation (table lookup)
interp3	3-D data interpolation (table lookup)
interpn	N-D data interpolation (table lookup)
mldivide $$ mrdivide /	Left or right matrix division
polyfit	Polynomial curve fitting
polyval	Polynomial evaluation

Fourier Transforms

abs	Absolute value and complex magnitude
angle	Phase angle
cplxpair	Sort complex numbers into complex conjugate pairs
fft	Discrete Fourier transform
fft2	2-D discrete Fourier transform
fftn	N-D discrete Fourier transform
fftshift	Shift zero-frequency component to center of spectrum
fftw	Interface to FFTW library run-time algorithm tuning control
ifft	Inverse discrete Fourier transform
ifft2	2-D inverse discrete Fourier transform
ifftn	N-D inverse discrete Fourier transform
ifftshift	Inverse FFT shift
nextpow2	Next higher power of 2
unwrap	Correct phase angles to produce smoother phase plots

Derivatives and Integrals

cumtrapz	Cumulative trapezoidal numerical integration
del2	Discrete Laplacian
diff	Differences and approximate derivatives

gradient	Numerical gradient
polyder	Polynomial derivative
polyint	Integrate polynomial analytically
trapz	Trapezoidal numerical integration

Time Series Objects

Utilities (p. 1-60)	Combine timeseries objects, query and set timeseries object properties, plot timeseries objects
Data Manipulation (p. 1-61)	Add or delete data, manipulate timeseries objects
Event Data (p. 1-62)	Add or delete events, create new timeseries objects based on event data
Descriptive Statistics (p. 1-62)	Descriptive statistics for timeseries objects

Utilities

get (timeseries)	Query timeseries object property values
getdatasamplesize	Size of data sample in timeseries object
getqualitydesc	Data quality descriptions
isempty (timeseries)	Determine whether timeseries object is empty
length (timeseries)	Length of time vector
plot (timeseries)	Plot time series
set (timeseries)	Set properties of timeseries object
size (timeseries)	Size of timeseries object

timeseries	Create timeseries object
tsdata.event	Construct event object for timeseries object
tsprops	Help on timeseries object properties
tstool	Open Time Series Tools GUI

Data Manipulation

addsample	Add data sample to timeseries object
ctranspose (timeseries)	Transpose timeseries object
delsample	Remove sample from timeseries object
detrend (timeseries)	Subtract mean or best-fit line and all NaNs from time series
filter (timeseries)	Shape frequency content of time series
getabstime (timeseries)	Extract date-string time vector into cell array
getinterpmethod	Interpolation method for timeseries object
getsampleusingtime (timeseries)	Extract data samples into new timeseries object
idealfilter (timeseries)	Apply ideal (noncausal) filter to timeseries object
resample (timeseries)	Select or interpolate timeseries data using new time vector
setabstime (timeseries)	Set times of timeseries object as date strings
setinterpmethod	Set default interpolation method for timeseries object

synchronize	Synchronize and resample two timeseries objects using common time vector
transpose (timeseries)	Transpose timeseries object
vertcat (timeseries)	Vertical concatenation of timeseries objects
Event Data	
addevent	Add event to timeseries object
delevent	Remove tsdata.event objects from timeseries object
gettsafteratevent	New timeseries object with samples occurring at or after event
gettsafterevent	New timeseries object with samples occurring after event
gettsatevent	New timeseries object with samples occurring at event
gettsbeforeatevent	New timeseries object with samples occurring before or at event
gettsbeforeevent	New timeseries object with samples occurring before event

Descriptive Statistics

gettsbetweenevents

Interquartile range of timeseries data
Maximum value of timeseries data
Mean value of timeseries data
Median value of timeseries data

New timeseries object with samples

occurring between events

min (timeseries)	Minimum value of timeseries data
std (timeseries)	Standard deviation of timeseries data
sum (timeseries)	Sum of timeseries data
var (timeseries)	Variance of timeseries data

Time Series Collections

Utilities (p. 1-63)	Query and set tscollection object properties, plot tscollection objects
Data Manipulation (p. 1-64)	Add or delete data, manipulate tscollection objects

Utilities

get (tscollection)	Query tscollection object property values
isempty (tscollection)	Determine whether tscollection object is empty
length (tscollection)	Length of time vector
plot (timeseries)	Plot time series
set (tscollection)	Set properties of tscollection object
size (tscollection)	Size of tscollection object
tscollection	Create tscollection object
tstool	Open Time Series Tools GUI

Data Manipulation

addsampletocollection	Add sample to $tscollection$ object
addts	Add timeseries object to tscollection object
delsamplefromcollection	Remove sample from tscollection object
getabstime (tscollection)	Extract date-string time vector into cell array
getsampleusingtime (tscollection)	Extract data samples into new tscollection object
gettimeseriesnames	Cell array of names of timeseries objects in tscollection object
horzcat (tscollection)	Horizontal concatenation for tscollection objects
removets	Remove timeseries objects from tscollection object
resample (tscollection)	Select or interpolate data in tscollection using new time vector
setabstime (tscollection)	Set times of tscollection object as date strings
settimeseriesnames	Change name of timeseries object in tscollection
vertcat (tscollection)	Vertical concatenation for tscollection objects

Programming and Data Types

Data Types (p. 1-65)	Numeric, character, structures, cell arrays, and data type conversion
Data Type Conversion (p. 1-74)	Convert one numeric type to another, numeric to string, string to numeric, structure to cell array, etc.
Operators and Special Characters (p. 1-76)	Arithmetic, relational, and logical operators, and special characters
Strings (p. 1-78)	Create, identify, manipulate, parse, evaluate, and compare strings
Bit-Wise Operations (p. 1-81)	Perform set, shift, and, or, compare, etc. on specific bit fields
Logical Operations (p. 1-82)	Evaluate conditions, testing for true or false
Relational Operations (p. 1-82)	Compare values for equality, greater than, less than, etc.
Set Operations (p. 1-83)	Find set members, unions, intersections, etc.
Date and Time Operations (p. 1-83)	Obtain information about dates and times
Programming in MATLAB (p. 1-84)	Function/expression evaluation, timed execution, memory, program control, error handling, MEX programming

Data Types

Numeric Types (p. 1-66)	Integer and floating-point data
Characters and Strings (p. 1-67)	Characters and arrays of characters
Structures (p. 1-68)	Data of varying types and sizes stored in fields of a structure

Cell Arrays (p. 1-69)	Data of varying types and sizes stored in cells of array
Map Container Objects (p. 1-70)	Select elements of Map container using indices of various data types
Function Handles (p. 1-71)	Invoke a function indirectly via handle
Java Classes and Objects (p. 1-71)	Access Java classes through MATLAB interface
Data Type Identification (p. 1-72)	Determine data type of a variable

Numeric Types

arrayfun	Apply function to each element of array
cast	Cast variable to different data type
cat	Concatenate arrays along specified dimension
class	Determine class name of object
find	Find indices and values of nonzero elements
intmax	Largest value of specified integer type
intmin	Smallest value of specified integer type
intwarning	Control state of integer warnings
ipermute	Inverse permute dimensions of N-D array
isa	Determine whether input is object of given class
isequal	Test arrays for equality

isequalwithequalnans	Test arrays for equality, treating NaNs as equal
isfinite	Array elements that are finite
isinf	Array elements that are infinite
isnan	Array elements that are NaN
isnumeric	Determine whether input is numeric array
isreal	Check if input is real array
isscalar	Determine whether input is scalar
isvector	Determine whether input is vector
permute	Rearrange dimensions of N-D array
realmax	Largest positive floating-point number
realmin	Smallest positive normalized floating-point number
reshape	Reshape array
squeeze	Remove singleton dimensions
zeros	Create array of all zeros

Characters and Strings

See "Strings" on page 1-78 for all string-related functions.

cellstr	Create cell array of strings from character array
char	Convert to character array (string)
eval	Execute string containing MATLAB expression
findstr	Find string within another, longer string

isstr	Determine whether input is character array
regexp, regexpi	Match regular expression
sprintf	Format data into string
sscanf	Read formatted data from string
strcat	Concatenate strings horizontally
strcmp, strcmpi	Compare strings
strfind	Find one string within another
strings	String handling
strjust	Justify character array
strmatch	Find possible matches for string
strread	Read formatted data from string
strrep	Find and replace substring
strtrim	Remove leading and trailing white space from string
strvcat	Concatenate strings vertically

Structures

arrayfun	Apply function to each element of array
cell2struct	Convert cell array to structure array
class	Determine class name of object
deal	Distribute inputs to outputs
fieldnames	Field names of structure, or public fields of object
getfield	Field of structure array
isa	Determine whether input is object of given class

isequal	Test arrays for equality
isfield	Determine whether input is structure array field
isscalar	Determine whether input is scalar
isstruct	Determine whether input is structure array
isvector	Determine whether input is vector
orderfields	Order fields of structure array
rmfield	Remove fields from structure
setfield	Assign values to structure array field
struct	Create structure array
struct2cell	Convert structure to cell array
structfun	Apply function to each field of scalar structure

Cell Arrays

cell	Construct cell array
cell2mat	Convert cell array of matrices to single matrix
cell2struct	Convert cell array to structure array
celldisp	Cell array contents
cellfun	Apply function to each cell in cell array
cellplot	Graphically display structure of cell array
cellstr	Create cell array of strings from character array
class	Determine class name of object
deal	Distribute inputs to outputs

isa	Determine whether input is object of given class
iscell	Determine whether input is cell array
iscellstr	Determine whether input is cell array of strings
isequal	Test arrays for equality
isscalar	Determine whether input is scalar
isvector	Determine whether input is vector
mat2cell	Divide matrix into cell array of matrices
num2cell	Convert numeric array to cell array
struct2cell	Convert structure to cell array

Map Container Objects

containers.Map	Construct containers.Map object
isKey (Map)	Check if containers.Map contains key
keys (Map)	Return all keys of containers.Map object
length (Map)	${ m Length} \ { m of} \ { m containers.Map} \ { m object}$
remove (Map)	Remove key-value pairs from containers.Map
size (Map)	size of containers.Map object
values (Map)	Return values of containers.Map object

Function Handles

class	Determine class name of object
feval	Evaluate function
func2str	Construct function name string from function handle
functions	Information about function handle
function_handle (@)	Handle used in calling functions indirectly
isa	Determine whether input is object of given class
isequal	Test arrays for equality
str2func	Construct function handle from function name string

Java Classes and Objects

cell	Construct cell array
class	Determine class name of object
clear	Remove items from workspace, freeing up system memory
depfun	List dependencies of function or P-file
exist	Check existence of variable, function, folder, or class
fieldnames	Field names of structure, or public fields of object
im2java	Convert image to Java image
import	Add package or class to current import list
inmem	Names of functions, MEX-files, Sun Java classes in memory

isa	Determine whether input is object of given class
isjava	Determine whether input is Sun Java object
javaaddpath	Add entries to dynamic Sun Java class path
javaArray	Construct Sun Java array
javachk	Generate error message based on Sun Java feature support
javaclasspath	Get and set Sun Java class path
javaMethod	Invoke Sun Java method
javaMethodEDT	Invoke Sun Java method from Event Dispatch Thread (EDT)
javaObject	Invoke Sun Java constructor, letting MATLAB choose the thread
javaObjectEDT	Invoke Sun Java object constructor on Event Dispatch Thread (EDT)
javarmpath	Remove entries from dynamic Sun Java class path
methods	Class method names
methodsview	View class methods
usejava	Determine whether Sun Java feature is supported in MATLAB software
which	Locate functions and files

Data Type Identification

is*	Detect state
isa	Determine whether input is object of given class

iscell	Determine whether input is cell array
iscellstr	Determine whether input is cell array of strings
ischar	Determine whether item is character array
isfield	Determine whether input is structure array field
isfloat	Determine whether input is floating-point array
ishghandle	True for Handle Graphics® object handles
isinteger	Determine whether input is integer array
isjava	Determine whether input is Sun Java object
islogical	Determine whether input is logical array
isnumeric	Determine whether input is numeric array
isobject	Is input MATLAB object
isreal	Check if input is real array
isstr	Determine whether input is character array
isstruct	Determine whether input is structure array
validateattributes	Check validity of array
who, whos	List variables in workspace

Data Type Conversion

Numeric (p. 1-74)	Convert data of one numeric type to another numeric type
String to Numeric (p. 1-74)	Convert characters to numeric equivalent
Numeric to String (p. 1-75)	Convert numeric to character equivalent
Other Conversions (p. 1-75)	Convert to structure, cell array, function handle, etc.

Numeric

cast	Cast variable to different data type
double	Convert to double precision
int8, int16, int32, int64	Convert to signed integer
single	Convert to single precision
typecast	Convert data types without changing underlying data
uint8, uint16, uint32, uint64	Convert to unsigned integer

String to Numeric

base2dec	Convert base N number string to decimal number
bin2dec	Convert binary number string to decimal number
cast	Cast variable to different data type
hex2dec	Convert hexadecimal number string to decimal number
hex2num	Convert hexadecimal number string to double-precision number

str2double	Convert string to double-precision value
str2num	Convert string to number
unicode2native	Convert Unicode [®] characters to numeric bytes

Numeric to String

cast	Cast variable to different data type
char	Convert to character array (string)
dec2base	Convert decimal to base N number in string
dec2bin	Convert decimal to binary number in string
dec2hex	Convert decimal to hexadecimal number in string
int2str	Convert integer to string
mat2str	Convert matrix to string
native2unicode	Convert numeric bytes to Unicode characters
num2str	Convert number to string

Other Conversions

cell2mat	Convert cell array of matrices to single matrix
cell2struct	Convert cell array to structure array
datestr	Convert date and time to string format
func2str	Construct function name string from function handle

1

logical	Convert numeric values to logical
mat2cell	Divide matrix into cell array of matrices
num2cell	Convert numeric array to cell array
num2hex	Convert singles and doubles to IEEE [®] hexadecimal strings
str2func	Construct function handle from function name string
str2mat	Form blank-padded character matrix from strings
struct2cell	Convert structure to cell array

Operators and Special Characters

Arithmetic Operators (p. 1-76)	Plus, minus, power, left and right divide, transpose, etc.
Relational Operators (p. 1-77)	Equal to, greater than, less than or equal to, etc.
Logical Operators (p. 1-77)	Element-wise and short circuit and, or, not
Special Characters (p. 1-78)	Array constructors, line continuation, comments, etc.

Arithmetic Operators

- Minus
- . Decimal point
- = Assignment
- * Matrix multiplication
- / Matrix right division

\mathbf{X}	Matrix left division
٨	Matrix power
,	Matrix transpose
.*	Array multiplication (element-wise)
./	Array right division (element-wise)
.\	Array left division (element-wise)
.^	Array power (element-wise)
; •	Array transpose

Relational Operators

<	Less than
<=	Less than or equal to
>	Greater than
>=	Greater than or equal to
==	Equal to
~=	Not equal to

Logical Operators

See also "Logical Operations" on page 1-82 for functions like xor, all, any, etc.

&&	Logical AND
	Logical OR
&	Logical AND for arrays
	Logical OR for arrays
~	Logical NOT

Special Characters

:	Create vectors, subscript arrays, specify for-loop iterations
()	Pass function arguments, prioritize operators
[]	Construct array, concatenate elements, specify multiple outputs from function
{}	Construct cell array, index into cell array
	Insert decimal point, define structure field, reference methods of object
.()	Reference dynamic field of structure
	Reference parent directory
	Continue statement to next line
,	Separate rows of array, separate function input/output arguments, separate commands
;	Separate columns of array, suppress output from current command
%	Insert comment line into code
%{ %}	Insert block of comments into code
!	Issue command to operating system
, ,	Construct character array
@	Construct function handle, reference class directory

Strings

Description of Strings in MATLAB (p. 1-79)	Basics of string handling in MATLAB
String Creation (p. 1-79)	Create strings, cell arrays of strings, concatenate strings together
String Identification (p. 1-79)	Identify characteristics of strings

String Manipulation (p. 1-80)	Convert case, strip blanks, replace characters
String Parsing (p. 1-80)	Formatted read, regular expressions, locate substrings
String Evaluation (p. 1-81)	Evaluate stated expression in string
String Comparison (p. 1-81)	Compare contents of strings

Description of Strings in MATLAB

strings

String handling

String Creation

blanks	Create string of blank characters
cellstr	Create cell array of strings from character array
char	Convert to character array (string)
sprintf	Format data into string
strcat	Concatenate strings horizontally
strvcat	Concatenate strings vertically

String Identification

isa	Determine whether input is object of given class
iscellstr	Determine whether input is cell array of strings
ischar	Determine whether item is character array
isletter	Array elements that are alphabetic letters

isscalar	Determine whether input is scalar
isspace	Array elements that are space characters
isstrprop	Determine whether string is of specified category
isvector	Determine whether input is vector
validatestring	Check validity of text string

String Manipulation

deblank	Strip trailing blanks from end of string
lower	Convert string to lowercase
strjust	Justify character array
strrep	Find and replace substring
strtrim	Remove leading and trailing white space from string
upper	Convert string to uppercase

String Parsing

Find string within another, longer string
Match regular expression
Replace string using regular expression
Translate string into regular expression
Read formatted data from string
Find one string within another

strread	Read formatted data from string
strtok	Selected parts of string

String Evaluation

eval	Execute string containing MATLAB expression
evalc	Evaluate MATLAB expression with capture
evalin	Execute MATLAB expression in specified workspace

String Comparison

strcmp, strcmpi	Compare strings
strmatch	Find possible matches for string
strncmp, strncmpi	Compare first ${\sf n}$ characters of strings

Bit-Wise Operations

bitand	Bitwise AND
bitcmp	Bitwise complement
bitget	Bit at specified position
bitmax	Maximum double-precision floating-point integer
bitor	Bitwise OR
bitset	Set bit at specified position
bitshift	Shift bits specified number of places
bitxor	Bitwise XOR
swapbytes	Swap byte ordering

1

Logical Operations

all	Determine whether all array elements are nonzero or true
and	Find logical AND of array or scalar inputs
any	Determine whether any array elements are nonzero
false	Logical 0 (false)
find	Find indices and values of nonzero elements
isa	Determine whether input is object of given class
iskeyword	Determine whether input is MATLAB keyword
isvarname	Determine whether input is valid variable name
logical	Convert numeric values to logical
not	Find logical NOT of array or scalar input
or	Find logical OR of array or scalar inputs
true	Logical 1 (true)
xor	Logical exclusive-OR

See "Operators and Special Characters" on page 1-76 for logical operators.

Relational Operations

eq	Test for equality
ge	Test for greater than or equal to

gt	Test for greater than
le	Test for less than or equal to
lt	Test for less than
ne	Test for inequality

See "Operators and Special Characters" on page 1-76 for relational operators.

Set Operations

intersect	Find set intersection of two vectors
ismember	Array elements that are members of set
issorted	Determine whether set elements are in sorted order
setdiff	Find set difference of two vectors
setxor	Find set exclusive OR of two vectors
union	Find set union of two vectors
unique	Find unique elements of vector

Date and Time Operations

addtodate	Modify date number by field
calendar	Calendar for specified month
clock	Current time as date vector
cputime	Elapsed CPU time
date	Current date string
datenum	Convert date and time to serial date number
datestr	Convert date and time to string format

datevec	Convert date and time to vector of components
eomday	Last day of month
etime	Time elapsed between date vectors
now	Current date and time
weekday	Day of week

Programming in MATLAB

Functions and Scripts (p. 1-85)	Write and execute program code, interact with caller, check input and output values, dependencies
Evaluation (p. 1-86)	Evaluate expression in string, apply function to array, run script file, etc.
Timer (p. 1-87)	Schedule execution of MATLAB commands
Variables and Functions in Memory (p. 1-88)	List, lock, or clear functions in memory, construct variable names, consolidate workspaces, refresh caches
Control Flow (p. 1-89)	Conditional control, loop control, error control, program termination
Error Handling (p. 1-90)	Generate warnings and errors, test for and catch errors, capture data on cause of error, warning control
MEX Programming (p. 1-91)	Compile MEX function from C or Fortran code, list MEX-files in memory, debug MEX-files

Functions and Scripts

addOptional (inputParser)	Add optional argument to Input Parser scheme
addParamValue (inputParser)	Add parameter name/value argument to Input Parser scheme
addRequired (inputParser)	Add required argument to Input Parser scheme
createCopy (inputParser)	Create copy of inputParser object
depdir	List dependent folders for function or P-file
depfun	List dependencies of function or P-file
echo	Display statements during function execution
end	Terminate block of code, or indicate last array index
function	Declare function
input	Request user input
inputname	Variable name of function input
inputParser	Construct input parser object
mfilename	File name of currently running function
namelengthmax	Maximum identifier length
nargchk	Validate number of input arguments
nargin, nargout	Number of function arguments
nargoutchk	Validate number of output arguments
parse (inputParser)	Parse and validate named inputs
pcode	Create protected function file

script	Sequence of MATLAB statements in file
syntax	Two ways to call MATLAB functions
varargin	Variable length input argument list
varargout	Variable length output argument list

Evaluation

ans	Most recent answer
arrayfun	Apply function to each element of array
assert	Generate error when condition is violated
builtin	Execute built-in function from overloaded method
cellfun	Apply function to each cell in cell array
echo	Display statements during function execution
eval	Execute string containing MATLAB expression
evalc	Evaluate MATLAB expression with capture
evalin	Execute MATLAB expression in specified workspace
feval	Evaluate function
iskeyword	Determine whether input is MATLAB keyword
isvarname	Determine whether input is valid variable name
pause	Halt execution temporarily

run	Run script that is not on current path
script	Sequence of MATLAB statements in file
structfun	Apply function to each field of scalar structure
symvar	Determine symbolic variables in expression
tic, toc	Measure performance using stopwatch timer

Timer

delete (timer)	Remove timer object from memory
disp (timer)	Information about timer object
get (timer)	Timer object properties
isvalid (timer)	Determine whether timer object is valid
set (timer)	Configure or display timer object properties
start	Start timer(s) running
startat	Start timer(s) running at specified time
stop	Stop timer(s)
timer	Construct timer object
timerfind	Find timer objects
timerfindall	Find timer objects, including invisible objects
wait	Wait until timer stops running

Variables and Functions in Memory

ans	Most recent answer
assignin	Assign value to variable in specified workspace
datatipinfo	Produce short description of input variable
genvarname	Construct valid variable name from string
global	Declare global variables
inmem	Names of functions, MEX-files, Sun Java classes in memory
isglobal	Determine whether input is global variable
memory	Display memory information
mislocked	Determine if function is locked in memory
mlock	Prevent clearing function from memory
munlock	Allow clearing functions from memory
namelengthmax	Maximum identifier length
pack	Consolidate workspace memory
persistent	Define persistent variable
rehash	Refresh function and file system path caches

Control Flow

break	Terminate execution of for or while loop
case	Execute block of code if condition is true
catch	Handle error detected in try-catch statement
continue	Pass control to next iteration of for or while loop
else	Execute statements if condition is false
elseif	Execute statements if additional condition is true
end	Terminate block of code, or indicate last array index
error	Display message and abort function
for	Execute statements specified number of times
if	Execute statements if condition is true
otherwise	Default part of switch statement
parfor	Parallel for-loop
return	Return to invoking function
switch	Switch among several cases, based on expression
try	Execute statements and catch resulting errors
while	Repeatedly execute statements while condition is true

Error Handling

addCause (MException)	Record additional causes of exception
assert	Generate error when condition is violated
catch	Handle error detected in try-catch statement
disp (MException)	Display MException object
eq (MException)	Compare MException objects for equality
error	Display message and abort function
ferror	Information about file I/O errors
getReport (MException)	Get error message for exception
intwarning	Control state of integer warnings
isequal (MException)	Compare MException objects for equality
last (MException)	Last uncaught exception
lastwarn	Last warning message
MException	Capture error information
ne (MException)	Compare MException objects for inequality
rethrow (MException)	Reissue existing exception
throw (MException)	Issue exception and terminate function
try	Execute statements and catch resulting errors
warning	Warning message

MEX Programming

dbmex	Enable MEX-file debugging (on UNIX platforms)
inmem	Names of functions, MEX-files, Sun Java classes in memory
mex	Compile MEX-function from C/C++ or Fortran source code
mex.getCompilerConfigurations	Get compiler configuration information for building MEX-files
mexext	Binary MEX-file name extension

1

Object-Oriented Programming

Classes and Objects (p. 1-92)	Get information about classes and objects
Handle Classes (p. 1-93)	Define and use handle classes
Events and Listeners (p. 1-94)	Define and use events and listeners
Meta-Classes (p. 1-94)	Access information about classes without requiring instances

Classes and Objects

class	Determine class name of object
classdef	Class definition keywords
exist	Check existence of variable, function, folder, or class
inferiorto	Specify inferior class relationship
isobject	Is input MATLAB object
loadobj	Modify load process for object
methods	Class method names
methodsview	View class methods
properties	Class property names
subsasgn	Subscripted assignment
subsindex	Subscript indexing with object
subsref	Redefine subscripted reference for objects
superiorto	Establish superior class relationship

Handle Classes

addlistener (handle)	Create event listener
addprop (dynamicprops)	Add dynamic property
delete (handle)	Handle object destructor function
dynamicprops	Abstract class used to derive handle class with dynamic properties
findobj (handle)	Find handle objects matching specified conditions
findprop (handle)	Find meta.property object associated with property name
get (hgsetget)	Query property values of handle objects derived from hgsetget class
getdisp (hgsetget)	Override to change command window display
handle	Abstract class for deriving handle classes
hgsetget	Abstract class used to derive handle class with set and get methods
isvalid (handle)	Is object valid handle class object
notify (handle)	Notify listeners that event is occurring
relationaloperators (handle)	Equality and sorting of handle objects
set (hgsetget)	Assign property values to handle objects derived from hgsetget class
setdisp (hgsetget)	Override to change command window display

Events and Listeners

addlistener (handle)	Create event listener
event.EventData	Base class for all data objects passed to event listeners
event.listener	Class defining listener objects
event.PropertyEvent	Listener for property events
event.proplistener	Define listener object for property events
events	Event names
notify (handle)	Notify listeners that event is occurring

Meta-Classes

meta.class	meta.class class describes MATLAB classes
meta.class.fromName	Return meta.class object associated with named class
meta.DynamicProperty	meta.DynamicProperty class describes dynamic property of MATLAB object
meta.event	meta.event class describes MATLAB class events
meta.method	meta.method class describes MATLAB class methods
meta.package	meta.package class describes MATLAB packages
meta.package.fromName	Return meta.package object for specified package
meta.package.getAllPackages	Get all top-level packages

meta.property

metaclass

meta.property class describes MATLAB class properties Obtain meta.class object 1

Graphics

Basic Plots and Graphs (p. 1-96)	Linear line plots, log and semilog plots
Plotting Tools (p. 1-97)	GUIs for interacting with plots
Annotating Plots (p. 1-97)	Functions for and properties of titles, axes labels, legends, mathematical symbols
Specialized Plotting (p. 1-98)	Bar graphs, histograms, pie charts, contour plots, function plotters
Bit-Mapped Images (p. 1-101)	Display image object, read and write graphics file, convert to movie frames
Printing (p. 1-102)	Printing and exporting figures to standard formats
Handle Graphics (p. 1-102)	Creating graphics objects, setting properties, finding handles

Basic Plots and Graphs

box	Axes border
errorbar	Plot error bars along curve
hold	Retain current graph in figure
line	Create line object
LineSpec (Line Specification)	Line specification string syntax
loglog	Log-log scale plot
plot	2-D line plot
plot3	3-D line plot
plotyy	2-D line plots with y-axes on both left and right side
polar	Polar coordinate plot

semilogx,	semilogy	
subplot		

Plotting Tools

figurepalette pan plotbrowser plotedit plottools propertyeditor rotate3d showplottool zoom Semilogarithmic plots Create axes in tiled positions

Show or hide figure palette Pan view of graph interactively Show or hide figure plot browser Interactively edit and annotate plots Show or hide plot tools Show or hide property editor Rotate 3-D view using mouse Show or hide figure plot tool Turn zooming on or off or magnify by factor

Annotating Plots

annotation	Create annotation objects
clabel	Contour plot elevation labels
datacursormode	Enable, disable, and manage interactive data cursor mode
datetick	Date formatted tick labels
gtext	Mouse placement of text in 2-D view
legend	Graph legend for lines and patches
rectangle	Create 2-D rectangle object
texlabel	Produce TeX format from character string

title	Add title to current axes
xlabel, ylabel, zlabel	Label <i>x</i> -, <i>y</i> -, and <i>z</i> -axis

Specialized Plotting

Area, Bar, and Pie Plots (p. 1-98)	1-D, 2-D, and 3-D graphs and charts
Contour Plots (p. 1-99)	Unfilled and filled contours in 2-D and 3-D
Direction and Velocity Plots (p. 1-99)	Comet, compass, feather and quiver plots
Discrete Data Plots (p. 1-99)	Stair, step, and stem plots
Function Plots (p. 1-99)	Easy-to-use plotting utilities for graphing functions
Histograms (p. 1-100)	Plots for showing distributions of data
Polygons and Surfaces (p. 1-100)	Functions to generate and plot surface patches in two or more dimensions
Scatter/Bubble Plots (p. 1-101)	Plots of point distributions
Animation (p. 1-101)	Functions to create and play movies of plots

Area, Bar, and Pie Plots

area	Filled area 2-D plot
bar, barh	Plot bar graph (vertical and horizontal)
bar3, bar3h	Plot 3-D bar chart
pareto	Pareto chart
pie	Pie chart
pie3	3-D pie chart

Contour Plots

contour	Contour plot of matrix
contour3	3-D contour plot
contourc	Low-level contour plot computation
contourf	Filled 2-D contour plot
ezcontour	Easy-to-use contour plotter
ezcontourf	Easy-to-use filled contour plotter

Direction and Velocity Plots

comet	2-D comet plot
comet3	3-D comet plot
compass	Plot arrows emanating from origin
feather	Plot velocity vectors
quiver	Quiver or velocity plot
quiver3	3-D quiver or velocity plot

Discrete Data Plots

stairs	Stairstep graph
stem	Plot discrete sequence data
stem3	Plot 3-D discrete sequence data

Function Plots

ezcontour	Easy-to-use contour plotter
ezcontourf	Easy-to-use filled contour plotter
ezmesh	Easy-to-use 3-D mesh plotter

ezmeshc	Easy-to-use combination mesh/contour plotter
ezplot	Easy-to-use function plotter
ezplot3	Easy-to-use 3-D parametric curve plotter
ezpolar	Easy-to-use polar coordinate plotter
ezsurf	Easy-to-use 3-D colored surface plotter
ezsurfc	Easy-to-use combination surface/contour plotter
fplot	Plot function between specified limits

Histograms

hist	Histogram plot
histc	Histogram count
rose	Angle histogram plot

Polygons and Surfaces

cylinder	Generate cylinder
delaunay	Delaunay triangulation
delaunay3	3-D Delaunay tessellation
delaunayn	N-D Delaunay tessellation
dsearch	Search Delaunay triangulation for nearest point
ellipsoid	Generate ellipsoid
fill	Filled 2-D polygons
fill3	Filled 3-D polygons

inpolygon	Points inside polygonal region
pcolor	Pseudocolor (checkerboard) plot
polyarea	Area of polygon
rectint	Rectangle intersection area
ribbon	Ribbon plot
slice	Volumetric slice plot
sphere	Generate sphere
waterfall	Waterfall plot

Scatter/Bubble Plots

plotmatrix	Scatter plot matrix
scatter	Scatter plot
scatter3	3-D scatter plot

Animation

frame2im	Return image data associated with movie frame
getframe	Capture movie frame
im2frame	Convert image to movie frame
movie	Play recorded movie frames
noanimate	Change EraseMode of all objects to normal

Bit-Mapped Images

frame2im	Return image data associated with movie frame
im2frame	Convert image to movie frame

im2java	Convert image to Java image
image	Display image object
imagesc	Scale data and display image object
imfinfo	Information about graphics file
imformats	Manage image file format registry
imread	Read image from graphics file
imwrite	Write image to graphics file
ind2rgb	Convert indexed image to RGB image

Printing

hgexport	Export figure
orient	Hardcopy paper orientation
print, printopt	Print figure or save to file and configure printer defaults
printdlg	Print dialog box
printpreview	Preview figure to print
saveas	Save figure or Simulink block diagram using specified format

Handle Graphics

Graphics Object Identification (p. 1-103)	Find and manipulate graphics objects via their handles
Object Creation (p. 1-104)	Constructors for core graphics objects
Annotation Objects (p. 1-104)	Property descriptions for annotation objects
Plot Objects (p. 1-105)	Property descriptions for plot objects

Figure Windows (p. 1-105)	Control and save figures
Axes Operations (p. 1-106)	Operate on axes objects
Object Property Operations (p. 1-106)	Query, set, and link object properties

Graphics Object Identification

allchild	Find all children of specified objects
ancestor	Ancestor of graphics object
copyobj	Copy graphics objects and their descendants
delete	Remove files or graphics objects
findall	Find all graphics objects
findfigs	Find visible offscreen figures
findobj	Locate graphics objects with specific properties
gca	Current axes handle
gcbf	Handle of figure containing object whose callback is executing
gcbo	Handle of object whose callback is executing
gco	Handle of current object
get	Query Handle Graphics object properties
ishandle	Determine whether input is valid Handle Graphics handle
propedit	Open Property Editor
set	Set Handle Graphics object properties

Object Creation

axes	Create axes graphics object
figure	Create figure graphics object
hggroup	Create hggroup object
hgtransform	Create hgtransform graphics object
image	Display image object
light	Create light object
line	Create line object
patch	Create one or more filled polygons
rectangle	Create 2-D rectangle object
root object	Root
surface	Create surface object
text	Create text object in current axes
uicontextmenu	Create context menu

Annotation Objects

Annotation Arrow Properties	Define annotation arrow properties
Annotation Doublearrow Properties	Define annotation doublearrow properties
Annotation Ellipse Properties	Define annotation ellipse properties
Annotation Line Properties	Define annotation line properties
Annotation Rectangle Properties	Define annotation rectangle properties
Annotation Textarrow Properties	Define annotation textarrow properties
Annotation Textbox Properties	Define annotation textbox properties

Plot Objects

Areaseries Properties Barseries Properties Contourgroup Properties Errorbarseries Properties Image Properties Lineseries Properties Quivergroup Properties Scattergroup Properties Stairseries Properties Stemseries Properties Surfaceplot Properties Define areaseries properties Define barseries properties Define contourgroup properties Define errorbarseries properties Define image properties Define lineseries properties Define quivergroup properties Define scattergroup properties Define stairseries properties Define stairseries properties Define stemseries properties

Figure Windows

clf	Clear current figure window
close	Remove specified figure
closereq	Default figure close request function
drawnow	Flush event queue and update figure window
gcf	Current figure handle
hgload	Load Handle Graphics object hierarchy from file
hgsave	Save Handle Graphics object hierarchy to file
newplot	Determine where to draw graphics objects
opengl	Control OpenGL [®] rendering

refresh	Redraw current figure
saveas	Save figure or Simulink block diagram using specified format

Axes Operations

axis	Axis scaling and appearance
box	Axes border
cla	Clear current axes
gca	Current axes handle
grid	Grid lines for 2-D and 3-D plots
ishold	Current hold state
makehgtform	Create 4-by-4 transform matrix

Object Property Operations

get	Query Handle Graphics object properties
linkaxes	Synchronize limits of specified 2-D axes
linkprop	Keep same value for corresponding properties
refreshdata	Refresh data in graph when data source is specified
set	Set Handle Graphics object properties

3-D Visualization

Surface and Mesh Plots (p. 1-107)	Plot matrices, visualize functions of two variables, specify colormap
View Control (p. 1-109)	Control the camera viewpoint, zooming, rotation, aspect ratio, set axis limits
Lighting (p. 1-111)	Add and control scene lighting
Transparency (p. 1-111)	Specify and control object transparency
Volume Visualization (p. 1-111)	Visualize gridded volume data

Surface and Mesh Plots

Surface and Mesh Creation (p. 1-107)	Visualizing gridded and triangulated data as lines and surfaces
Domain Generation (p. 1-108)	Gridding data and creating arrays
Color Operations (p. 1-108)	Specifying, converting, and manipulating color spaces, colormaps, colorbars, and backgrounds

Surface and Mesh Creation

hidden	Remove hidden lines from mesh plot
mesh, meshc, meshz	Mesh plots
peaks	Example function of two variables
surf, surfc	3-D shaded surface plot
surface	Create surface object
surfl	Surface plot with colormap-based lighting
tetramesh	Tetrahedron mesh plot

trimesh	Triangular mesh plot
triplot	2-D triangular plot
trisurf	Triangular surface plot

Domain Generation

meshgrid

Generate X and Y arrays for 3-D plots

Color Operations

brighten	Brighten or darken colormap
caxis	Color axis scaling
colorbar	Colorbar showing color scale
colordef	Set default property values to display different color schemes
colormap	Set and get current colormap
colormapeditor	Start colormap editor
ColorSpec (Color Specification)	Color specification
contrast	Grayscale colormap for contrast enhancement
graymon	Set default figure properties for grayscale monitors
hsv2rgb	Convert HSV colormap to RGB colormap
rgb2hsv	Convert RGB colormap to HSV colormap
rgbplot	Plot colormap
shading	Set color shading properties
spinmap	Spin colormap

surfnorm	Compute and display 3-D surface normals
whitebg	Change axes background color

View Control

Camera Viewpoint (p. 1-109)	Orbiting, dollying, pointing, rotating camera positions and setting fields of view
Aspect Ratio and Axis Limits (p. 1-110)	Specifying what portions of axes to view and how to scale them
Object Manipulation (p. 1-110)	Panning, rotating, and zooming views
Region of Interest (p. 1-110)	Interactively identifying rectangular regions

Camera Viewpoint

camdolly	Move camera position and target
cameratoolbar	Control camera toolbar programmatically
camlookat	Position camera to view object or group of objects
camorbit	Rotate camera position around camera target
campan	Rotate camera target around camera position
campos	Set or query camera position
camproj	Set or query projection type
camroll	Rotate camera about view axis
camtarget	Set or query location of camera target

camup	Set or query camera up vector
camva	Set or query camera view angle
camzoom	Zoom in and out on scene
makehgtform	Create 4-by-4 transform matrix
view	Viewpoint specification
viewmtx	View transformation matrices

Aspect Ratio and Axis Limits

daspect	Set or query axes data aspect ratio
pbaspect	Set or query plot box aspect ratio
xlim, ylim, zlim	Set or query axis limits

Object Manipulation

pan	Pan view of graph interactively
reset	Reset graphics object properties to their defaults
rotate	Rotate object in specified direction
rotate3d	Rotate 3-D view using mouse
selectmoveresize	Select, move, resize, or copy axes and uicontrol graphics objects
zoom	Turn zooming on or off or magnify by factor

Region of Interest

dragrect	Drag rectangles with mouse
rbbox	Create rubberband box for area
	selection

1-110

Lighting

camlight	Create or move light object in camera coordinates
diffuse	Calculate diffuse reflectance
light	Create light object
lightangle	Create or position light object in spherical coordinates
lighting	Specify lighting algorithm
material	Control reflectance properties of surfaces and patches
specular	Calculate specular reflectance

Transparency

alim	Set or query axes alpha limits
alpha	Set transparency properties for objects in current axes
alphamap	Specify figure alphamap (transparency)

Volume Visualization

coneplot	Plot velocity vectors as cones in 3-D vector field
contourslice	Draw contours in volume slice planes
curl	Compute curl and angular velocity of vector field
divergence	Compute divergence of vector field
flow	Simple function of three variables

interpstreamspeed	Interpolate stream-line vertices from flow speed
isocaps	Compute isosurface end-cap geometry
isocolors	Calculate isosurface and patch colors
isonormals	Compute normals of isosurface vertices
isosurface	Extract isosurface data from volume data
reducepatch	Reduce number of patch faces
reducevolume	Reduce number of elements in volume data set
shrinkfaces	Reduce size of patch faces
slice	Volumetric slice plot
smooth3	Smooth 3-D data
stream2	Compute 2-D streamline data
stream3	Compute 3-D streamline data
streamline	Plot streamlines from 2-D or 3-D vector data
streamparticles	Plot stream particles
streamribbon	3-D stream ribbon plot from vector volume data
streamslice	Plot streamlines in slice planes
streamtube	Create 3-D stream tube plot
subvolume	Extract subset of volume data set
surf2patch	Convert surface data to patch data
volumebounds	Coordinate and color limits for volume data

GUI Development

Predefined Dialog Boxes (p. 1-113)	Dialog boxes for error, user input, waiting, etc.
User Interface Deployment (p. 1-114)	Open GUIs, create the handles structure
User Interface Development (p. 1-114)	Start GUIDE, manage application data, get user input
User Interface Objects (p. 1-115)	Create GUI components
Objects from Callbacks (p. 1-116)	Find object handles from within callbacks functions
GUI Utilities (p. 1-116)	Move objects, wrap text
Program Execution (p. 1-117)	Wait and resume based on user input

Predefined Dialog Boxes

dialog	Create and display empty dialog box
errordlg	Create and open error dialog box
export2wsdlg	Export variables to workspace
helpdlg	Create and open help dialog box
inputdlg	Create and open input dialog box
listdlg	Create and open list-selection dialog box
msgbox	Create and open message box
printdlg	Print dialog box
printpreview	Preview figure to print
questdlg	Create and open question dialog box
uigetdir	Open standard dialog box for selecting directory

uigetfile	Open standard dialog box for retrieving files
uigetpref	Open dialog box for retrieving preferences
uiopen	Open file selection dialog box with appropriate file filters
uiputfile	Open standard dialog box for saving files
uisave	Open standard dialog box for saving workspace variables
uisetcolor	Open standard dialog box for setting object's ColorSpec
uisetfont	Open standard dialog box for setting object's font characteristics
waitbar	Open or update a wait bar dialog box
warndlg	Open warning dialog box

User Interface Deployment

guidata	Store or retrieve GUI data
guihandles	Create structure of handles
movegui	Move GUI figure to specified location on screen
openfig	Open new copy or raise existing copy of saved figure

User Interface Development

addpref	Add preference
getappdata	Value of application-defined data
getpref	Preference

ginput	Graphical input from mouse or cursor
guidata	Store or retrieve GUI data
guide	Open GUI Layout Editor
inspect	Open Property Inspector
isappdata	True if application-defined data exists
ispref	Test for existence of preference
rmappdata	Remove application-defined data
rmpref	Remove preference
setappdata	Specify application-defined data
setpref	Set preference
uigetpref	Open dialog box for retrieving preferences
uisetpref	Manage preferences used in uigetpref
waitfor	Wait for condition before resuming execution
waitforbuttonpress	Wait for key press or mouse-button click

User Interface Objects

menu	Generate menu of choices for user input
uibuttongroup	Create container object to exclusively manage radio buttons and toggle buttons
uicontextmenu	Create context menu
uicontrol	Create user interface control object

uimenu	Create menus on figure windows
uipanel	Create panel container object
uipushtool	Create push button on toolbar
uitable	Create 2-D graphic table GUI component
uitoggletool	Create toggle button on toolbar
uitoolbar	Create toolbar on figure

Objects from Callbacks

findall	Find all graphics objects
findfigs	Find visible offscreen figures
findobj	Locate graphics objects with specific properties
gcbf	Handle of figure containing object whose callback is executing
gcbo	Handle of object whose callback is executing

GUI Utilities

align	Align user interface controls (uicontrols) and axes
getpixelposition	Get component position in pixels
listfonts	List available system fonts
selectmoveresize	Select, move, resize, or copy axes and uicontrol graphics objects
setpixelposition	Set component position in pixels

textwrap	Wrapped string matrix for given uicontrol
uistack	Reorder visual stacking order of objects
Program Execution	

uiresume

uiwait

Resume execution of blocked M-file Block execution and wait for resume 1

External Interfaces

Shared Libraries (p. 1-118)	Access functions stored in external shared library files
Java (p. 1-119)	Work with objects constructed from Java API and third-party class packages
.NET (p. 1-120)	Work with objects constructed from .NET assemblies
Component Object Model and ActiveX (p. 1-121)	Integrate COM components into your application
Web Services (p. 1-123)	Communicate between applications over a network using SOAP and WSDL
Serial Port Devices (p. 1-124)	Read and write to devices connected to your computer's serial port

See also *MATLAB C/C++* and *Fortran API Reference* for functions you can use in external routines that interact with MATLAB programs and the data in MATLAB workspaces.

Shared Libraries

calllib	Call function in shared library
libfunctions	Return information on functions in shared library
libfunctionsview	View functions in shared library
libisloaded	Determine if shared library is loaded
libpointer	Create pointer object for use with shared libraries
libstruct	Create structure pointer for use with shared libraries

oadlibrary	Load shared library into MATLAB software
unloadlibrary	Unload shared library from memory

Java

class	Determine class name of object
fieldnames	Field names of structure, or public fields of object
import	Add package or class to current import list
inspect	Open Property Inspector
isa	Determine whether input is object of given class
isjava	Determine whether input is Sun Java object
javaaddpath	Add entries to dynamic Sun Java class path
javaArray	Construct Sun Java array
javachk	Generate error message based on Sun Java feature support
javaclasspath	Get and set Sun Java class path
javaMethod	Invoke Sun Java method
javaMethodEDT	Invoke Sun Java method from Event Dispatch Thread (EDT)
javaObject	Invoke Sun Java constructor, letting MATLAB choose the thread
javaObjectEDT	Invoke Sun Java object constructor on Event Dispatch Thread (EDT)
javarmpath	Remove entries from dynamic Sun Java class path

methods	Class method names
methodsview	View class methods
usejava	Determine whether Sun Java feature is supported in MATLAB software

.NET

enable NET from Network Drive	Enable access to .NET commands from network drive
NET.addAssembly	Make .NET assembly visible to MATLAB
NET.Assembly	Members of .NET assembly
NET.convertArray	Convert numeric MATLAB array to .NET array
NET.createArray	Create single or multidimensional .NET array
NET.createGeneric	Create instance of specialized .NET generic type
NET.GenericClass	Represent parameterized generic type definitions
NET.GenericClass	Constructor for NET.GenericClass class
${\it NET.invokeGenericMethod}$	Invoke generic method of object
NET.NetException	.NET exception
NET.setStaticProperty	Static property or field name

Component Object Model and ActiveX

actxcontrol	Create Microsoft [®] ActiveX [®] control in figure window
actxcontrollist	List currently installed Microsoft ActiveX controls
actxcontrolselect	Create Microsoft ActiveX control from GUI
actxGetRunningServer	Handle to running instance of Automation server
actxserver	Create COM server
addproperty	Add custom property to COM object
delete (COM)	Remove COM control or server
deleteproperty	Remove custom property from COM object
enableservice	Enable, disable, or report status of MATLAB Automation server
eventlisteners	List event handler functions associated with COM object events
events (COM)	List of events COM object can trigger
Execute	Execute MATLAB command in Automation server
Feval (COM)	Evaluate MATLAB function in Automation server
fieldnames	Field names of structure, or public fields of object
get (COM)	Get property value from interface, or display properties
GetCharArray	Character array from Automation server
GetFullMatrix	Matrix from Automation server workspace

GetVariable	Data from variable in Automation server workspace
GetWorkspaceData	Data from Automation server workspace
inspect	Open Property Inspector
interfaces	List custom interfaces exposed by COM server object
invoke	Invoke method on COM object or interface, or display methods
isa	Determine whether input is object of given class
iscom	Determine whether input is COM or ActiveX object
isevent	Determine whether input is COM object event
isinterface	Determine whether input is COM interface
ismethod	Determine whether input is COM object method
isprop	Determine whether input is COM object property
load (COM)	Initialize control object from file
MaximizeCommandWindow	Open Automation server window
methods	Class method names
methodsview	View class methods
MinimizeCommandWindow	Minimize size of Automation server window
move	Move or resize control in parent window
propedit (COM)	Open built-in property page for control

PutCharArray	Store character array in Automation server
PutFullMatrix	Matrix in Automation server workspace
PutWorkspaceData	Data in Automation server workspace
Quit (COM)	Terminate MATLAB Automation server
registerevent	Associate event handler for COM object event at run time
release	Release COM interface
save (COM)	Serialize control object to file
set (COM)	Set object or interface property to specified value
unregisterallevents	Unregister all event handlers associated with COM object events at run time
unregisterevent	Unregister event handler associated with COM object event at run time

Web Services

callSoapService	Send SOAP message to endpoint
createClassFromWsdl	Create MATLAB class based on WSDL document
createSoapMessage	Create SOAP message to send to server
parseSoapResponse	Convert response string from SOAP server into MATLAB types

Serial Port Devices

clear (serial)	Remove serial port object from MATLAB workspace
delete (serial)	Remove serial port object from memory
fgetl (serial)	Read line of text from device and discard terminator
fgets (serial)	Read line of text from device and include terminator
fopen (serial)	Connect serial port object to device
fprintf (serial)	Write text to device
fread (serial)	Read binary data from device
fscanf (serial)	Read data from device, and format as text
fwrite (serial)	Write binary data to device
get (serial)	Serial port object properties
instrcallback	Event information when event occurs
instrfind	Read serial port objects from memory to MATLAB workspace
instrfindall	Find visible and hidden serial port objects
isvalid (serial)	Determine whether serial port objects are valid
length (serial)	Length of serial port object array
load (serial)	Load serial port objects and variables into MATLAB workspace
readasync	Read data asynchronously from device
record	Record data and event information to file

save (serial)	Save serial port objects and variables to file
serial	Create serial port object
serialbreak	Send break to device connected to serial port
set (serial)	Configure or display serial port object properties
size (serial)	Size of serial port object array
stopasync	Stop asynchronous read and write operations

2

Alphabetical List

Arithmetic Operators + - * $/ \setminus ^ '$ Relational Operators < > <= >= == ~= Logical Operators: Elementwise & | ~ Logical Operators: Short-circuit && || Special Characters [] () $\{\} = '...., ;: \% ! @$ colon (:) abs accumarray acos acosd acosh acot acotd acoth acsc acscd acsch actxcontrol actxcontrollist actx control selectactxGetRunningServer actxserver addCause (MException) addevent addframe (avifile) addlistener (handle) addOptional (inputParser) addParamValue (inputParser)

addpath addpref addprop (dynamicprops) addproperty addRequired (inputParser) addsample addsampletocollection addtodate addts airy align alim all allchild alpha alphamap amd ancestor and angle annotation Annotation Arrow Properties Annotation Doublearrow Properties Annotation Ellipse Properties Annotation Line Properties Annotation Rectangle Properties Annotation Textarrow Properties Annotation Textbox Properties ans any area Areaseries Properties arrayfun ascii asec asecd asech

asin asind asinh assert assignin atan atan2 atand atanh audiodevinfo audioplayer audiorecorder aufinfo auread auwrite avifile aviinfo aviread axes **Axes** Properties axis balance bar, barh bar3, bar3h **Barseries** Properties baryToCart base2dec beep bench besselh besseli besselj besselk bessely beta betainc betaincinv

betaln bicg bicgstab bicgstabl bin2dec binary bitand bitcmp bitget bitmax bitor bitset bitshift bitxor blanks blkdiag box break brighten brush bsxfun builddocsearchdb builtin bvp4c bvp5c bvpget bvpinit bvpset bvpxtend calendar calllib callSoapService camdolly cameratoolbarcamlight camlookat camorbit

campan campos camproj camroll camtarget camup camva camzoom cartToBary cart2pol cart2sph case cast cat catch caxis cd convexHull cd (ftp) cdf2rdf cdfepoch cdfinfo cdflib cdflib.close cdflib.closeVar cdflib.computeEpochcdflib.computeEpoch16cdflib.create cdflib.createAttr cdflib.createVar cdflib.delete cdflib.deleteAttr cdflib.deleteAttrEntry cdflib.deleteAttrgEntry cdflib.deleteVar cdflib.deleteVarRecords cdflib.epoch16Breakdown **2** Alphabetical List

cdflib.epochBreakdown cdflib.getAttrEntry cdflib.getAttrgEntry cdflib.getAttrMaxEntry cdflib.getAttrMaxgEntry cdflib.getAttrName cdflib.getAttrNum cdflib.getAttrScope cdflib.getCacheSize cdflib.getChecksum cdflib.getCompression cdflib.getCompressionCacheSize cdflib.getConstantNames cdflib.getConstantValue cdflib.getCopyright cdflib.getFormat cdflib.getLibraryCopyright cdflib.getLibraryVersion cdflib.getMajority cdflib.getName cdflib.getNumAttrEntries cdflib.getNumAttrgEntries cdflib.getNumAttributes cdflib.getNumgAttributes cdflib.getReadOnlyMode cdflib.getStageCacheSize cdflib.getValidate cdflib.getVarAllocRecords cdflib.getVarBlockingFactor cdflib.getVarCacheSize cdflib.getVarCompression cdflib.getVarData cdflib.getVarMaxAllocRecNum cdflib.getVarMaxWrittenRecNumcdflib.getVarName cdflib.getVarNum cdflib.getVarNumRecsWritten

cdflib.getVarPadValue cdflib.getVarRecordData cdflib.getVarReservePercent cdflib.getVarSparseRecords cdflib.getVersion cdflib.hyperGetVarData cdflib.hyperPutVarData cdflib.inquire cdflib.inquireAttr cdflib.inquireAttrEntry cdflib.inquireAttrgEntry cdflib.inquireVar cdflib.open cdflib.putAttrEntry cdflib.putAttrgEntry cdflib.putVarData cdflib.putVarRecordData cdflib.renameAttr cdflib.renameVar cdflib.setCacheSize cdflib.setChecksum cdflib.setCompression cdflib.setCompressionCacheSize cdflib.setFormat cdflib.setMajority cdflib.setReadOnlyMode cdflib.setStageCacheSize cdflib.setValidate cdflib.setVarAllocBlockRecords cdflib.setVarBlockingFactor cdflib.setVarCacheSize cdflib.setVarCompression cdflib.setVarInitialRecs cdflib.setVarPadValue cdflib.SetVarReservePercent cdflib.setVarsCacheSize cdflib.setVarSparseRecords

cdfread cdfwrite ceil cell cell2mat cell2struct celldisp cellfun cellplot $\operatorname{cellstr}$ cgs char checkin checkout chol cholinc cholupdate circshift circumcenters cla clabel class classdef clc clear clearvars clear (serial) clf clipboard clock close close close (avifile) close (ftp) closereq cmopts cmpermute

cmunique colamd colorbar colordef colormap colormapeditor ColorSpec (Color Specification) colperm comet comet3 commandhistory commandwindow compan compass complex computeStrip computeTile computer cond condeig condest coneplot conj continue contour contour3 contourc contourf **Contourgroup Properties** contourslice contrast conv conv2convhull convhulln convn copyfile

copyobj corrcoef \cos $\cos d$ \cosh \cot cotd coth cov cplxpair cputime create (RandStream) createClassFromWsdl createCopy (inputParser) createSoapMessage cross \csc cscd csch csvread csvwrite ctranspose (timeseries) cumprod cumsum cumtrapz curl currentDirectory customverctrl cylinder daqread daspect datacursormode datatipinfo date datenum datestr datetick

datevec dbclear dbcont dbdown dblquad dbmex dbquit dbstack dbstatus dbstep dbstop dbtype dbup dde23 ddeget ddesd ddeset deal deblank dec2base dec2bin dec2hex decic deconv del2DelaunayTri DelaunayTri delaunay delaunay3 delaunayn delete delete (COM) delete (ftp) delete (handle) delete (serial) delete (timer) deleteproperty

delevent delsample delsamplefromcollection demo depdir depfun det detrend detrend (timeseries) deval diag dialog diary diff diffuse dir dir (ftp) disp disp (memmapfile) disp (MException) disp (serial) disp (timer) display dither divergence dlmread dlmwrite dmperm doc docsearch dos dot double dragrect drawnow dsearch dsearchn

dynamicprops echo echodemo edgeAttachments edges edit eig eigs ellipj ellipke ellipsoid else elseif enableNETfromNetworkDrive enableservice end eomday eps eq eq (MException) erf, erfc, erfcx, erfinv, erfcinv error errorbar **Errorbarseries** Properties errordlg etime etree etreeplot eval evalc evalin event.EventData event.listener event.PropertyEvent event.proplistener eventlisteners events

events (COM) Execute exifread exist exit exp expint expm expm1export2wsdlg eye ezcontour ezcontourf ezmesh ezmeshc ezplot ezplot3 ezpolar ezsurf ezsurfc faceNormals factor factorial false fclose fclose (serial) feather featureEdges feof ferror feval Feval (COM) fftfft2fftn fftshift fftw

fgetl fgetl (serial) fgets fgets (serial) fieldnames figure **Figure Properties** figurepalette fileattrib filebrowser File Formats filemarker fileparts fileread filesep fill fill3 filter filter (timeseries) filter2 find findall findfigs findobj findobj (handle) findprop (handle) findstr finish fitsinfo fitsread fix flipdim fliplr flipud floor flow fminbnd

fminsearch fopen fopen (serial) for format fplot fprintf fprintf (serial) frame2im fread fread (serial) freeBoundary freqspace frewind fscanf fscanf (serial) fseek ftell ftp full fullfile func2str function function_handle (@) functions funm fwrite fwrite (serial) fzero gallery gamma, gammainc, gammaln gammaincinv gca gcbf gcbo gcd gcf

gcoge genpath genvarname get get get get (COM) get (hgsetget) get (memmapfile) get get (RandStream) get (serial) get (timer) get (timeseries) get (tscollection) getabstime (timeseries) getabstime (tscollection) getappdata getaudiodata GetCharArray getdatasamplesize getDefaultStream (RandStream) getdisp (hgsetget) getenv getfield getFileFormats getframe GetFullMatrix getinterpmethod getpixelposition getpref getqualitydesc getReport (MException) getsampleusingtime (timeseries) getsampleusingtime (tscollection) getTag

getTagNames gettimeseriesnames gettsafteratevent gettsafterevent gettsatevent gettsbeforeatevent gettsbeforeevent gettsbetweenevents GetVariable getVersion GetWorkspaceData ginput global gmres gplot grabcode gradient graymon grid griddata griddata3 griddatan gsvd \mathbf{gt} gtext guidata guide guihandles gunzip gzip hadamard handle hankel hdf hdf5 hdf5info hdf5read

2-18

hdf5write hdfinfo hdfread hdftool help helpbrowser helpdesk helpdlg helpwin hess hex2dec hex2num hgexport hggroup **Hggroup** Properties hgload hgsave hgsetget hgtransform Hgtransform Properties hidden hilb hist histc hold home horzcat horzcat (tscollection) hostid hsv2rgb hypot i idealfilter (timeseries) idivide if ifft ifft2

2 Alphabetical List

ifftn ifftshift ilu im2frame im2java imag image **Image Properties** imagesc imapprox imfinfo imformats import importdata imread imwrite incenters inOutStatus ind2rgb ind2sub Inf inferiorto info inline inmem inpolygon input inputdlg inputname inputParser inspect instrcallback instrfind instrfindall int2str int8, int16, int32, int64 interfaces

interp1 interp1q interp2 interp3 interpft interpn interpstreamspeed intersect intmax intmin intwarning inv invhilb invoke ipermute iqr (timeseries) is* isa isappdata iscell iscellstr ischar iscom isdir isEdge isempty isempty (timeseries) isempty (tscollection) isequal isequal (MException) isequalwithequalnans isevent isfield isfinite isfloat isglobal ishandle

ishghandle ishold isinf isinteger isinterface isjava isKey (Map) iskeyword isletter islogical ismac ismember ismethod isnan isnumeric isobject isocaps isocolors isonormals isosurface ispc isPlatformSupported ispref isprime isprop isreal isscalar issorted isspace issparse isstr isstrprop isstruct isstudent isTiled isunix isvalid (handle)

isvalid (serial) isvalid (timer) isvarname isvector j javaaddpath javaArray javachk javaclasspath javaMethod javaMethodEDT javaObject javaObjectEDT javarmpath keyboard keys (Map) kron last (MException) lastDirectory lasterr lasterror lastwarn lcm ldl ldivide, rdivide le legend legendre length length (Map) length (serial) length (timeseries) length (tscollection) libfunctions libfunctionsview libisloaded libpointer

libstruct license light **Light Properties** lightangle lighting lin2mu line Line Properties Lineseries Properties LineSpec (Line Specification) linkaxes linkdata linkprop linsolve linspace list (RandStream) listdlg listfonts load load (COM) load (serial) loadlibrary loadobj log $\log 10$ log1p $\log 2$ logical loglog logm logspace lookfor lower lslscov

lsqr lt lu luinc magic makehgtform containers.Map mat2cell mat2str material matlabcolon (matlab:) matlabrc matlabroot matlab (UNIX) matlab (Windows) max max (timeseries) MaximizeCommandWindow maxNumCompThreads mean mean (timeseries) median median (timeseries) memmapfile memory menu mesh, meshc, meshz meshgrid meta.class meta.class.fromName meta.DynamicProperty meta.event meta.method meta.package meta.package.fromName meta.package.getAllPackagesmeta.property

metaclass methods methodsview mex mex.getCompilerConfigurations MException mexext mfilename mget min min (timeseries) MinimizeCommandWindow minres mislocked mkdir mkdir (ftp) mkpp mldivide \setminus , mrdivide / mlint mlintrpt mlock mmfileinfo mmreader mod mode more move movefile movegui movie movie2avi mput msgbox mtimes mu2lin multibandread multibandwrite

munlock namelengthmax NaN nargchk nargin, nargout nargoutchk native2unicode nchoosek ndgrid ndims ne nearestNeighbor ne (MException) neighbors NET NET.addAssembly NET.Assembly NET.convertArray NET.createArray NET.createGeneric NET.GenericClass NET.GenericClass NET.invokeGenericMethod NET.NetException NET.setStaticProperty netcdf netcdf.abort netcdf.close netcdf.copyAtt netcdf.create netcdf.defDim netcdf.defVar netcdf.delAtt netcdf.endDefnetcdf.getAtt netcdf.getConstantnetcdf.getConstantNames

netcdf.getVar netcdf.inq netcdf.inqAtt netcdf.ingAttID netcdf.inqAttName netcdf.inqDim netcdf.ingDimID netcdf.inqLibVers netcdf.inqVar netcdf.inqVarID netcdf.open netcdf.putAtt netcdf.putVar netcdf.reDef netcdf.renameAtt netcdf.renameDim netcdf.renameVar netcdf.setDefaultFormat netcdf.setFillnetcdf.sync newplot nextDirectory nextpow2 nnz noanimate nonzeros norm normest not notebook notify (handle) now nthroot null num2cell num2hex num2str

numberOfStrips numberOfTiles numel nzmax ode15i ode23, ode45, ode113, ode15s, ode23s, ode23t, ode23tb odefile odeget odeset odextend onCleanup ones open openfig opengl openvar optimget optimset or ordeig orderfields ordqz ordschur orient orth otherwise pack padecoef pagesetupdlg pan pareto parfor parse (inputParser) parseSoapResponse pascal patch **Patch Properties**

2 Alphabetical List

path path2rc pathsep pathtool pause pbaspect pcg pchip pcode pcolor pdepe pdeval peaks perl perms permute persistent pi pie pie3 pinv planerot play play playblocking playshow plot plot (timeseries) plot3 plotbrowser plotedit plotmatrix plottools plotyy pointLocation pol2cart polar

poly polyarea polyder polyeig polyfit polyint polyval polyvalm pow2 power ppval prefdir preferences primes print, printopt printdlg printpreview prod profile profsave propedit propedit (COM) properties propertyeditor psi publish PutCharArray PutFullMatrix PutWorkspaceData pwd qmr $\mathbf{q}\mathbf{r}$ qrdelete qrinsert qrupdate quad quad2d

quadgk quadl quadv questdlg quit Quit (COM) quiver quiver3 **Quivergroup** Properties $\mathbf{q}\mathbf{z}$ rand rand (RandStream) randi randi (RandStream) randn randn (RandStream) randperm randperm (RandStream) RandStream RandStream (RandStream) rank rat, rats rbbox rcond read read readasync readEncodedStrip readEncodedTile real reallog realmax realmin realpow realsqrt record record

recordblocking rectangle **Rectangle Properties** rectint recycle reducepatch reducevolume refresh refreshdata regexp, regexpi regexprep regexptranslate registerevent rehash release relationaloperators (handle) rem remove (Map) removets rename repmat resample (timeseries) resample (tscollection) reset reset (RandStream) reshape residue restored efault pathrethrow rethrow (MException) return rewriteDirectory rgb2hsv rgb2ind rgbplot ribbon rmappdata

2 Alphabetical List

rmdir rmdir (ftp) rmfield rmpath rmpref root object **Root Properties** roots rose rosser rot90 rotate rotate3d round rref rsf2csf run save save (COM) save (serial) saveas saveobj savepath scatter scatter3 Scattergroup Properties schur script sec secd sech selectmoveresize semilogx, semilogy sendmail serial serialbreak set

set set set (COM) set (hgsetget) set set (RandStream) set (serial) set (timer) set (timeseries) set (tscollection) setabstime (timeseries) setabstime (tscollection) setappdata setDefaultStream (RandStream) setdiff setDirectory setdisp (hgsetget) setenv setfield setinterpmethod setpixelposition setpref setstr setSubDirectory setTag settimeseriesnames setxor shading shg shiftdim showplottool shrinkfaces sign \sin sind single sinh

size size (Map) size (serial) size (timeseries) size size (tscollection) slice smooth3snapnow sort sortrows sound soundsc spalloc sparse spaugment $\operatorname{spconvert}$ spdiags specular speye spfun sph2cart sphere spinmap spline spones spparms sprand sprandn sprandsym sprank sprintf $_{\rm spy}$ sqrt sqrtm squeeze ss2tf

sscanf stairs **Stairseries Properties** start startat startup std std (timeseries) stem stem3 **Stemseries** Properties stop stopasync str2double str2func str2mat str2num strcat strcmp, strcmpi stream2 stream3 streamline streamparticles streamribbon streamslice streamtube strfind strings strjust strmatch strncmp, strncmpi strread strrep strtok strtrim struct struct2cell

structfun strvcat sub2ind subplot subsasgn subsindex subspace subsref substruct subvolume sum sum (timeseries) superclasses superiorto support surf, surfc surf2patch surface Surface Properties Surfaceplot Properties surfl surfnorm svd \mathbf{svds} swapbytes switch symamd symbfact symmlq symrcm symvar synchronize syntax system tan tand tanh

tar tempdir tempname tetramesh texlabel text **Text Properties** textread textscan textwrap tfqmr throw (MException) throwAsCaller (MException) tic, toc Tiff timer timerfind timerfindall timeseries title todatenum toeplitz toolboxdir trace transpose (timeseries) trapz treelayout treeplot tril trimesh triplequad triplot TriRep TriRep TriScatteredInterp TriScatteredInterp trisurf

triu true try tscollection tsdata.event tsearch tsearchn tsprops tstool type typecast uibuttongroup **Uibuttongroup** Properties uicontextmenu **Uicontextmenu** Properties uicontrol **Uicontrol Properties** uigetdir uigetfile uigetpref uiimport uimenu **Uimenu** Properties uint8, uint16, uint32, uint64 uiopen uipanel **Uipanel** Properties uipushtool **Uipushtool Properties** uiputfile uiresume uisave uisetcolor uisetfont uisetpref uistack uitable

Uitable Properties uitoggletool **Uitoggletool Properties** uitoolbar **Uitoolbar** Properties uiwait undocheckout unicode2native union unique unix unloadlibrary unmesh unmkpp unregisterallevents unregisterevent untar unwrap unzip upper urlread urlwrite usejava userpath validateattributes validatestring values (Map) vander var var (timeseries) varargin varargout vectorize ver verctrl verLessThan version

vertcat vertcat (timeseries) vertcat (tscollection) vertexAttachments view viewmtx visdiff volumebounds voronoi voronoiDiagram voronoin wait waitbar waitfor waitforbuttonpress warndlg warning waterfall wavfinfo wavplay wavread wavrecord wavwrite web weekday what whatsnew which while whitebg who, whos wilkinson winopen winqueryreg wk1finfo wk1read wk1write

workspace write writeDirectory writeEncodedStrip writeEncodedTile xlabel, ylabel, zlabel xlim, ylim, zlim xlsfinfo xlsread xlswrite xmlread xmlwrite xor xslt zeros zip zoom

pack

Purpose	Consolidate workspace memory
Syntax	pack pack filename pack('filename')
Description	pack frees up needed space by reorganizing information so that it only uses the minimum memory required. All variables from your base and global workspaces are preserved. Any persistent variables that are defined at the time are set to their default value (the empty matrix, []).
	The MATLAB software temporarily stores your workspace data in a file called tp######.mat (where ###### is a numeric value) that is located in your temporary folder. (You can use the command dir(tempdir) to see the files in this folder).
	pack filename frees space in memory, temporarily storing workspace data in a file specified by filename. This file resides in your current working folder and, unless specified otherwise, has a .mat file extension.
	<pre>pack('filename') is the function form of pack.</pre>
Remarks	You can only run pack from the MATLAB command line.
	If you specify a filename argument, that file must reside in a folder for which you have write permission.
	The pack function does not affect the amount of memory allocated to the MATLAB process. You must quit MATLAB to free up this memory.
	Since MATLAB uses a heap method of memory management, extended MATLAB sessions may cause memory to become fragmented. When memory is fragmented, there may be plenty of free space, but not enough contiguous memory to store a new large variable.
	If you get the Out of memory message from MATLAB, the pack function may find you some free memory without forcing you to delete variables.
	The pack function frees space by

	• Saving all variables in the base and global workspaces to a temporary file.
	• Clearing all variables and functions from memory.
	• Reloading the base and global workspace variables back from the temporary file and then deleting the file.
	If you use pack and there is still not enough free memory to proceed, you must clear some variables. If you run out of memory often, you can allocate larger matrices earlier in the MATLAB session and use these system-specific tips:
	• When running MATLAB on The Open Group UNIX platforms, ask your system manager to increase your swap space.
	• On Microsoft Windowsplatforms, increase virtual memory using the Windows Control Panel.
	To maintain persistent variables when you run pack, use mlock in the function.
Examples	Change the current folder to one that is writable, run pack, and return to the previous folder.
	<pre>cwd = pwd; cd(tempdir); pack cd(cwd)</pre>
See Also	clear, memory

padecoef

Purpose	Padé approximation of time delays
Syntax	[num,den] = padecoef(T,N)
Description	[num,den] = padecoef(T,N) returns the Nth-order Padé approximation of the continuous-time delay T in transfer function form. The row vectors num and den contain the numerator and denominator coefficients in descending powers of T . Both are Nth-order polynomials. Class support for input T :
	float: double, single
Class Support	Input T support floating-point values of type single or double.
References	[1] Golub, G. H. and C. F. Van Loan <i>Matrix Computations</i> , 3rd ed. Johns Hopkins University Press, Baltimore: 1996, pp. 572–574.
See Also	pade

PurposePage setup dialog box

Syntax dlg = pagesetupdlg(fig)

Note This function is obsolete. Use printpreview instead.

Description dlg = pagesetupdlg(fig) creates a dialog box from which a set of pagelayout properties for the figure window, fig, can be set.

pagesetupdlg implements the "Page Setup..." option in the Figure File Menu.

pagesetupdlg supports setting the layout for a single figure. fig must be a single figure handle, not a vector of figures or a simulink diagram.

Page Setup - Figure 1	X
Size and Position Paper Lines and Text Mode Use screen size, centered on page Use manual size and position Manual size and position Top: 2.50 Use defaults Left: 0.25 Fill page Width: 8.00 Fix aspect ratio Height: 6.00 Center	t Axes and Figure
Units: inches	OK Cancel

See Also printdlg, printpreview, printopt

Purpose	Pan view of graph interactively
GUI Alternatives	Use the Pan tool on the figure toolbar to enable and disable pan mode on a plot, or select Pan from the figure's Tools menu. For details, see "Panning — Shifting Your View of the Graph" in the MATLAB Graphics documentation.
Syntax	pan on pan xon pan yon pan off pan pan(figure_handle,) h = pan(figure_handle)
Description	<pre>pan on turns on mouse-based panning in the current figure. pan xon turns on panning only in the x direction in the current figure. pan yon turns on panning only in the y direction in the current figure. pan off turns panning off in the current figure on or off. pan(figure_handle,) sets the pan state in the specified figure. h = pan(figure_handle) returns the figure's pan mode object for the figure figure_handle for you to customize the mode's behavior. Using Pan Mode Objects Access the following properties of pan mode objects via get and modify some of them using set: Enable 'on' 'off' — Specifies whether this figure mode is currently enabled on the figure Motion 'horizontal' 'vertical' 'both' — The type of panning enabled for the figure </pre>

• FigureHandle <handle> — The associated figure handle, a read-only property that cannot be set

Pan Mode Callbacks

You can program the following callbacks for pan mode operations.

• ButtonDownFilter <function_handle> — Function to intercept ButtonDown events

The application can inhibit the panning operation under circumstances the programmer defines, depending on what the callback returns. The input function handle should reference a function with two implicit arguments (similar to Handle Graphics object callbacks):

```
function [res] = myfunction(obj,event_obj)
% obj handle to the object that has been clicked on
% event_obj event data (empty in this release)
% res [output] a logical flag to determine whether the pan
% operation should take place or the 'ButtonDownFcn'
% property of the object should take precedence
```

 ActionPreCallback <function_handle> — Function to execute before panning

Set this callback to if you need to execute code when a pan operation begins. The function handle should reference a function with two implicit arguments (similar to Handle Graphics object callbacks):

function myfunction(obj,event_obj)
% obj handle to the figure that has been clicked on
% event_obj object containing struct of event data

The event data struct has the following field:

Axes The handle of the axes that is being panned

ActionPostCallback <function_handle> — Function to execute after panning

Set this callback if you need to execute code when a pan operation ends. The function handle should reference a function with two implicit arguments (similar to Handle Graphics object callbacks):

<pre>function myfunction(obj,event_obj)</pre>							
% obj	handle to the figure that has been clicked on						
% event_obj	object containing struct of event data (same as the						
%	event data of the 'ActionPreCallback' callback)						

Pan Mode Utility Functions

The following functions in pan mode query and set certain of its properties.

• flags = isAllowAxesPan(h,axes) — Function querying permission to pan axes

Calling the function isAllowAxesPan on the pan object, h, with a vector of axes handles, axes, as input returns a logical array of the same dimension as the axes handle vector, which indicates whether a pan operation is permitted on the axes objects.

• setAllowAxesPan(h,axes,flag) — Function to set permission to pan axes

Calling the function setAllowAxesPan on the pan object, h, with a vector of axes handles, axes, and a logical scalar, flag, either allows or disallows a pan operation on the axes objects.

• *info* = getAxesPanMotion(h,axes) — Function to get style of pan operations

Calling the function getAxesPanMotion on the pan object, h, with a vector of axes handles, axes, as input will return a character cell array of the same dimension as the axes handle vector, which indicates the type of pan operation for each axes. Possible values for the type of operation are 'horizontal', 'vertical' or 'both'. setAxesPanMotion(h,axes,style) — Function to set style of pan operations

Calling the function setAxesPanMotion on the pan object, h, with a vector of axes handles, axes, and a character array, style, sets the style of panning on each axes.

Examples Example 1 – Entering Pan Mode

Plot a graph and turn on Pan mode:

```
plot(magic(10));
pan on
% pan on the plot
```

Example 2 – Constrained Pan

Constrain pan to *x*-axis using set:

```
plot(magic(10));
h = pan;
set(h,'Motion','horizontal','Enable','on');
% pan on the plot in the horizontal direction.
```

Example 3 – Constrained Pan in Subplots

Create four axes as subplots and give each one a different panning behavior:

```
ax1 = subplot(2,2,1);
plot(1:10);
h = pan;
ax2 = subplot(2,2,2);
plot(rand(3));
setAllowAxesPan(h,ax2,false);
ax3 = subplot(2,2,3);
plot(peaks);
setAxesPanMotion(h,ax3,'horizontal');
ax4 = subplot(2,2,4);
```

```
contour(peaks);
setAxesPanMotion(h,ax4,'vertical');
% pan on the plots.
```

Example 4 – Coding a ButtonDown Callback

Create a buttonDown callback for pan mode objects to trigger. Copy the following code to a new file, execute it, and observe panning behavior:

```
function demo
% Allow a line to have its own 'ButtonDownFcn' callback.
hLine = plot(rand(1, 10));
set(hLine, 'ButtonDownFcn', 'disp(''This executes'')');
set(hLine, 'Tag', 'DoNotIgnore');
h = pan;
set(h, 'ButtonDownFilter',@mycallback);
set(h, 'Enable', 'on');
% mouse click on the line
%
function [flag] = mycallback(obj,event obj)
% If the tag of the object is 'DoNotIgnore', then return true.
% Indicate what the target is
disp(['Clicked ' get(obj,'Type') ' object'])
objTag = get(obj, 'Tag');
if strcmpi(objTag, 'DoNotIgnore')
   flag = true;
else
   flag = false;
end
```

Example 5 – Coding Pre- and Post-Callback Behavior

Create callbacks for pre- and post-ButtonDown events for pan mode objects to trigger. Copy the following code to a new file, execute it, and observe panning behavior:

function demo % Listen to pan events

```
plot(1:10);
h = pan;
set(h, 'ActionPreCallback',@myprecallback);
set(h, 'ActionPostCallback',@mypostcallback);
set(h, 'Enable', 'on');
%
function myprecallback(obj,evd)
disp('A pan is about to occur.');
%
function mypostcallback(obj,evd)
newLim = get(evd.Axes, 'XLim');
msgbox(sprintf('The new X-Limits are [%.2f %.2f].',newLim));
```

Example 6 – Creating a Context Menu for Pan Mode

Coding a context menu that lets the user to switch to Zoom mode by right-clicking:

You cannot add items to the built-in pan context menu, but you can replace it with your own.

Remarks You can create a pan mode object once and use it to customize the behavior of different axes, as Example 3 illustrates. You can also change its callback functions on the fly.

	Note Do not change figure callbacks within an interactive mode. While a mode is active (when panning, zooming, etc.), you will receive a warning if you attempt to change any of the figure's callbacks and the operation will not succeed. The one exception to this rule is the figure WindowButtonMotionFcn callback, which can be changed from within a mode. Therefore, if you are creating a GUI that updates a figure's callbacks, the GUI should some keep track of which interactive mode is active, if any, before attempting to do this.
	When you assign different pan behaviors to different subplot axes via a mode object and then link them using the linkaxes function, the behavior of the axes you manipulate with the mouse carries over to the linked axes, regardless of the behavior you previously set for the other axes.
See Also	zoom, linkaxes, rotate3d "Object Manipulation" on page 1-110 for related functions


pareto

eto chart



GUI Alternatives	To graph selected variables, use the Plot Selector plot(t,y) - in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.
Syntax	<pre>pareto(Y) pareto(Y,names) pareto(Y,X) H = pareto()</pre>
Description	<pre>Pareto charts display the values in the vector Y as bars drawn in descending order. Values in Y must be nonnegative and not include NaNs. Only the first 95% of the cumulative distribution is displayed. pareto(Y) labels each bar with its element index in Y and also plots a line displaying the cumulative sum of Y. pareto(Y,names) labels each bar with the associated name in the string matrix or cell array names. pareto(Y,X) labels each bar with the associated value from X. pareto(ax,) plots a Pareto chart in existing axes ax rather than GCA. H = pareto() returns a combination of patch and line object handles.</pre>
Examples	Example 1: Examine the cumulative productivity of a group of programmers to see how normal its distribution is:

```
codelines = [200 120 555 608 1024 101 57 687];
coders = ...
{'Fred','Ginger','Norman','Max','Julia','Wally','Heidi','Pat'};
pareto(codelines, coders)
title('Lines of Code by Programmer')
```



Example 2:


Generate a vector, X, representing diagnostic codes with values from 1 to 10 indicating various faults on devices emerging from a production line:

X = min(round(abs(randn(100,1)*4))+1,10);

Plot a Pareto chart showing the frequency of failure for each diagnostic code from the most to the least common:

pareto(hist(X))

pareto



Remarks You can use pareto to display the output of hist, even for vectors that include negative numbers. Because only the first 95 percent of values are displayed, one or more of the smallest bars may not appear. If you extend the Xlim of your chart, you can display all the values, but the new bars will not be labeled.

You cannot place datatips (use the Datacursor tool) on graphs created with pareto.

See Also hist, bar

```
Purpose
                   Parallel for-loop
Syntax
                   parfor loopvar = initval:endval; statements; end
                   parfor (loopvar = initval:endval, M); statements; end
Description
                   parfor loopvar = initval:endval; statements; end executes a
                   series of MATLAB commands denoted here as statements for values of
                   loopvar between initval and endval, inclusive, which specify a vector
                   of increasing integer values. Unlike a traditional for-loop, there is no
                   guarantee of the order in which the loop iterations are executed.
                   The general format of a parfor statement is:
                      parfor loopvar = initval:endval
                           <statements>
                      end
                   Certain restrictions apply to the statements to ensure that the
                   iterations are independent, so that they can execute in parallel. If
                   you have the Parallel Computing Toolbox<sup>™</sup> software, the iterations of
                   statements can execute in parallel on separate MATLAB workers on
                   your multi-core computer or computer cluster.
                   To execute the loop body in parallel, you must open a pool of MATLAB
                   workers using the matlabpool function, which is available in Parallel
                   Computing Toolbox.
                   parfor (loopvar = initval:endval, M); statements; end
                   executes statements in a loop using a maximum of M MATLAB workers
                   to evaluate statements in the body of the parfor-loop. Input variable
                   M must be a nonnegative integer. By default, MATLAB uses up to as
                   many workers as it finds available.
                   When any of the following are true, MATLAB does not execute the loop
                   in parallel:
                    • There are no workers in a MATLAB pool
                    • You set M to zero
```

parfor

	• You do not have Parallel Computing Toolbox						
	If you have Parallel Computing Toolbox, you can read more about parfor and matlabpool by typing						
	doc distcomp/parfor doc distcomp/matlabpool						
Examples	Perform three large eigenvalue computations using three computers or cores:						
	matlabpool(3) parfor i=1:3, c(:,i) = eig(rand(1000)); end						
See Also	for						

Parse and validate named inputs						
p.parse(arglist) parse(p, arglist)						
p.parse(arglist) is part of the input argument checking mechanism employed by the MATLAB Input Parser utility. Input Parser code residing in a function that receives data from calling functions identifies what types of arguments are acceptable. The parse function parses and validates the inputs named in arglist.						
parse(p, arglist) is functionally the same as the syntax above.						
For more information on the inputParser class, see "Validating Inputs with Input Parser" in the MATLAB Programming Fundamentals documentation.						
This example writes a function called photoPrint that uses the Input Parser to check arguments passed to it. This function accepts up to eight input arguments. When called with the full set of inputs, the syntax is:						
photoPrint(filename, format, finish, colorCode, 'horizDim', hDim, 'vertDim', vDim);						
Only the first two of these inputs are defined as required arguments; the rest are optional. The 'horizDim' and 'vertDim' arguments are in parameter name/value format. Pair the 'horizDim' parameter name with its value <i>hDim</i> , and likewise the 'vertDim' name with its value <i>vDim</i> . Here are several possible calling syntaxes for the function:						
<pre>photoPrint(filename, format); photoPrint(filename, format, finish) photoPrint(filename, format, finish, colorCode) photoPrint(filename, format, finish, colorCode, 'horizDim', hDim) photoPrint(filename, format, finish, colorCode, 'vertDim', vDim)</pre>						

Begin writing the example function photoPrint by entering the following two statements into a file named photoPrint.m. The second statement calls the class constructor for inputParser to create an instance p of the class. This class instance, or object, gives you access to all of the methods and properties of the class:

```
function photoPrint(filename, format, varargin)
p = inputParser; % Create an instance of the class.
```

Add the following code to the photoPrint function. These statements call the addRequired, addOptional, and addParamValue methods to define the types of input data one can pass to this function:

```
p.addRequired('filename', @ischar);
p.addRequired('format', @(x)strcmp(x,'jpeg')
    || strcmp(x,'tiff'));
p.addOptional('finish', 'glossy', @(x)strcmpi(x,'flat') ...
    || strcmpi(x,'glossy'));
p.addOptional('colorCode', 'CMYK', @(x)strcmpi(x,'CMYK') ...
    || strcmpi(x,'RGB'));
p.addParamValue('horizDim', 6, @(x)isnumeric(x) && x<=20));
p.addParamValue('vertDim', 4, @(x)isnumeric(x) && x<=20));</pre>
```

Just after this, call the parse method to parse and validate the inputs. MATLAB puts the results of the parse into a property named Results:

```
p.parse(filename, format, varargin{:});
p.Results
```

Save and execute the file, passing the required and any number of the optional input arguments. Examining p.Results displays the name of each input as a field, and the value of each input as the value of that field:

The following inputs have been received and validated: colorCode: 'RGB' filename: 'myPhoto' finish: 'flat' format: 'tiff' horizDim: 10 vertDim: 8

See Also inputParser, addRequired(inputParser), addOptional(inputParser), addParamValue(inputParser), createCopy(inputParser)

parseSoapResponse

Purpose	Convert response string from SOAP server into MATLAB types							
Syntax	parseSoapResponse(response)							
Description	parseSoapResponse(response) extracts data from response a string returned by a SOAP server from the callSoapService function, and converts it to appropriate MATLAB classes (types).							
Examples	This example uses parseSoapResponse in conjunction with other SOAP functions to retrieve information about books from a library database, specifically, the author's name for a given book title.							
	Note The example does not use an actual endpoint; therefore, you cannot run it. The example only illustrates how to use the SOAP functions.							
	<pre>% Create the message: message = createSoapMessage('urn:LibraryCatalog', 'getAuthor', {'In the Fall'}, {'In the Fall'}, {'http://www.w3.org/2001/XMLSchema}string'}, 'rpc'); % % Send the message to the service and get the response: response = callSoapService('http://test/soap/services/LibraryCatalog', 'urn:LibraryCatalog#getAuthor', message) % % Extract MATLAB data from the response author = parseSoapResponse(response) MATLAB returns:</pre>							

author = Kate Alvin

where author is a char class (type).

See Also callSoapService, createClassFromWsdl, createSoapMessage, urlread, xmlread

"Using Web Services with MATLAB" in the MATLAB External Interfaces documentation

pascal

Purpose	Pascal	matrix	Σ				
Syntax	<pre>A = pascal(n) A = pascal(n,1) A = pascal(n,2)</pre>						
Description	A = pascal(n) returns the Pascal matrix of order n: a symmetric positive definite matrix with integer entries taken from Pascal's triangle. The inverse of A has integer entries.						
	A = pascal(n,1) returns the lower triangular Cholesky factor (up to the signs of the columns) of the Pascal matrix. It is <i>involutary</i> , that is, it is its own inverse.						
	-				transposed and permuted version of to f the identity matrix.		
Examples	pascal(4) returns						
	1	1	1	1			
		2	3	4			
	1	3	6	10			
	1	4	10	20			
	A = pascal(3,2) produces						
	A =						
		1	1	1			
		-2	1 -1	0			
		1	0	0			
See Also	chol						

Purpose	Create one or more filled polygons			
Syntax	<pre>patch(X,Y,C) patch(X,Y,Z,C) patch(FV) patch(X,Y,C,'PropertyName',propertyvalue) patch('PropertyName',propertyvalue,) handle = patch()</pre>			
Properties	For a list of properties, see Patch Properties.			
Description	<pre>patch(X,Y,C) adds a filled 2-D patch object to the current axes. A patch object is one or more polygons defined by the coordinates of its vertices. The elements of X and Y specify the vertices of a polygon. If X and Y are m-by-n matrices, MATLAB draws n polygons with m vertices. C determines the color of the patch. For more information on color input requirements, see "Coloring Patches" on page 2-2905.</pre>			
	MATLAB does not require each face to have the same number of vertices. In cases where they do not, pad the end of the Faces matrix with NaNs. To define a patch with faces that do not close, add one or more NaNs to the row in the Vertices matrix that defines the vertex you do not want connected.			
	See "Creating 3-D Models with Patches" in <i>MATLAB 3-D Visualization</i> for more information on using patch objects.			
	patch(X,Y,Z,C) creates a patch in 3-D coordinates. If the coordinate data does not define closed polygons, patch closes the polygons. The data can define concave or intersecting polygons. However, if the edges of an individual patch face intersect themselves, the resulting face might be only partly filled. In that case, it is better to divide the face into smaller polygons.			
	patch(FV) creates a patch using structure FV, which contains the fields vertices, faces, and optionally facevertexcdata. These fields correspond to the Vertices, Faces, and FaceVertexCData patch properties. Specifying only unique vertices and their connection matrix			

can reduce the size of the data for patches having many faces. For an example of how to specify patches with this method, see "Specifying Patch Object Shapes" on page 2-2902.

patch(X,Y,C, 'PropertyName', propertyvalue...) follows the X, Y, (Z), and C arguments with property name/property value pairs to specify additional patch properties. For a description of the properties, see Patch Properties. You can specify properties as property name/property value pairs, structure arrays, and cell arrays (see the set and get reference pages for examples of how to specify these data types).

patch ('*PropertyName*', propertyvalue,...) specifies all properties using property name/property value pairs. This form lets you omit the color specification because MATLAB uses the default face color and edge color unless you explicitly assign a value to the FaceColor and EdgeColor properties. This form also lets you specify the patch using the Faces and Vertices properties instead of *x*-, *y*-, and *z*-coordinates. See "Specifying Patch Object Shapes" on page 2-2902 for more information.

handle = patch(...) returns the handle of the patch object it creates.

Unlike high-level area creation functions, such as fill or area, patch does not check the settings of the figure and axes NextPlot properties. It simply adds the patch object to the current axes.

Examples Specifying Patch Object Shapes


The next two examples create a patch object using two methods:

- Specifying *x*-, *y*-, and *z*-coordinates and color data (XData, YData, ZData, and CData properties)
- Specifying vertices, the connection matrix, and color data (Vertices, Faces, and FaceVertexCData properties)

Create five triangular faces, each having three vertices, by specifying the *x*-, *y*-, and *z*-coordinates of each vertex:


xdata = [2 2 0 2 5;

patch



Create the five triangular faces, specifying faces and vertices:

```
% The Vertices property contains the coordinates of each
% unique vertex defining the patch. The Faces property
% specifies how to connect these vertices to form each
% face of the patch. More than one face may use a given vertex.
% For this example, five triangles have 11 total vertices,
\% instead of 15. Each row contains the x- and y-coordinates
% of each vertex.
verts = [2 4; ...
        2 8; ...
        8 4; ...
        8 0; ...
        0 4; ...
        2 6; ...
        2 2; ...
        4 2; ...
        4 0; ...
        5 2; ...
        50];
% There are five faces, defined by connecting the
% vertices in the order indicated.
faces = [ ...
        1 2 3; ...
        1 3 4; ...
        5 6 1; ...
        7 8 9; ...
        11 10 4 ];
% Create the patch by specifying the Faces, Vertices,
% and FaceVertexCData properties as well as the
% FaceColor property. Red numbers denote the vertex
% numbers, as defined in faces. Blue indicate face numbers.
p =
patch('Faces',faces,'Vertices',verts,'FaceColor','w');
```



% Using the previous values for verts and faces, you can % create the same patch object using a structure: patchinfo.Vertices = verts; patchinfo.Faces = faces; patchinfo.FaceColor = 'w';

patch(patchinfo);

Coloring Patches

There are many ways to customize your patch objects using colors. The appropriate input depends on:

- Whether you want to change the edge colors
- How you specified the patch faces:
 - Using face/vertex values

• Using *x*-, *y*-, and *z*-coordinates

The following sections present the various options available.

Specifying Edge Colors

The following options apply to the edge colors of your patch object. The settings are independent of the face colors, but the colors themselves depend on the colors specified at each vertex. Markers show the color at each vertex. Specify the colors using the EdgeColor property. To explore the options using the Sample Input Code, first start with a base patch object:

xda	ta =	[2	2	0	2	5;	
		2	8	2	4	5;	
		8	8	2	4	8];	
yda	ta =	[4	4	4	2	0;	
		8	4	6	2	2;	
		4	0	4	0	0];	
cda	ta =	[15	0	4	6	10;	
		1	2	5	7	9;	
		2	3	0	8	3];	
n = natch/ydata ydata cdata 'Marker' 'o'							

p = patch(xdata,ydata,cdata,'Marker','o','MarkerFaceColor','flat','Fac

For more detailed information on how the EdgeColor property works, see the Patch Properties page.

Desired Look	EdgeColor Value	Sample Code
All edges have the same color, around all faces. This option does not rely on the FaceColor value.	ColorSpec	<pre>set(p,'EdgeColor','g')</pre>

Desired Look	EdgeColor Value	Sample Code
Each edge corresponds to the color of the vertex that precedes the edge, with one color per edge. This option requires that the FaceColor property be flat or interp. By default, if you specify CData when creating the patch object, its FaceColor property is interp.	'flat'	set(p,'EdgeColor','flat', 'LineWidth',3)

Desired Look	EdgeColor Value	Sample Code
Each edge corresponds to the vertex colors, interpolated between vertices. This option requires that the FaceColor property be flat or interp. By default, if you specify CData when creating the patch object, its FaceColor property is interp.	'interp'	<pre>set(gcf, 'Renderer', 'zbuffer') set(p, 'EdgeColor', 'interp', 'LineWidth',5)</pre>
Edges have no color. This option does not rely on the FaceColor value. If set, markers retain vertex colors.	'none'	<pre>set(p,'EdgeColor','none')</pre>

Desired	l Look					
۴ſ	•					
7 -						
6 -	•					
5-						
4	•					•
3-						
2 -	•	•	•			
1-						
	2 3	4	5	6	7	8

Specifying Face Colors Using Face/Vertex Input Matrics

The following options apply to the face colors of your patch object when you specify the faces using face/vertex input matrices. To explore the options, first start with a base patch object:

```
% For this example, there are five triangles (m = 5) sharing
% eleven unique vertices (k = 11).
verts = [2 4; ...
        2 8; ...
        8 4; ...
        8 0; ...
        0 4; ...
        2 6; ...
        2 2; ...
        4 2; ...
        4 0; ...
        5 2; ...
        50];
faces = [1 2 3; ...
         1 3 4; ...
         5 6 1; ...
         7 8 9; ...
         11 10 4];
```

```
p = patch('Faces',faces,'Vertices',verts,'FaceColor','b');
```

For more information on the relevant properties, see FaceColor, FaceVertexCData, and CDataMapping.

Desired Look	Parameter Values	Sample Code
All faces have the same color.	 FaceColor: ColorSpec FaceVertexCData: [] (no input) An empty array is the default value, and patch ignores any input until you set FaceColor to 'flat' or 'interp'. Color source: truecolor CDataMapping: 'direct' or 'scaled'. 	<pre>set(p,'FaceColor','r') Or set(p,'FaceColor',[1 0 0])</pre>
	'scaled' is the default value, but neither affects the outcome.	
Each face has a single, unique color, indexed from a selected section of the colormap.	 FaceColor: 'flat' FaceVertexCData: m-by-1 matrix of index values Color source: A selected 	clear cdata set(gca,'CLim',[O 4O]) cdata = [15 30 25 2 6O]'; set(p,'FaceColor','flat',
	portion of the colormap • CDataMapping: 'scaled'	'FaceVertexCData',cdata 'CDataMapping','scaled')

Desired Look	Parameter Values	Sample Code
Each face has a single, unique color, indexed from the whole colormap.	 FaceColor: 'flat' FaceVertexCData: m-by-1 matrix of index values Color source: colormap CDataMapping: 'direct' 'scaled' is the default value when you input CData values. If you want to change the axes CLim property, but want your patch object to index the entire colormap, use 'CDataMapping', 'direct'. 	<pre>clear cdata set(gca,'CLim',[0 40]) cdata = [15 30 25 2 60]'; set(p,'FaceColor','flat', 'FaceVertexCData',cdata, 'CDataMapping','direct')</pre>
Each face has a single, unique color, determined by truecolor value input.	 FaceColor: 'flat' FaceVertexCData: m-by-3 matrix of truecolor values, from 0 to 1 Color source: truecolor CDataMapping: 'direct' or 'scaled'. 'scaled' is the default value, but neither affects the outcome. 	clear cdata cdata = [0 0 1 0 0.8; 0 1 0 0 0.8; 1 0 1 0 0.8]'; set(p,'FaceColor','flat', 'FaceVertexCData',cdata)

patch

Desired Look	Parameter Values	Sample Code
Each unique vertex has a single, unique color, indexed from a selected section of the colormap. Faces each have a single, unique color, but edges may have 'flat' or 'interp' color.	 FaceColor: 'flat' FaceVertexCData: k-by-1 matrix of index values Color source: A selected portion of the colormap CDataMapping: 'scaled' 	<pre>clear cdata set(gca,'CLim',[0 40]) cdata = [15 30 25 2 60 12 23 40 13 26 24]'; set(p,'FaceColor','flat', 'FaceVertexCData',cdata, 'EdgeColor','flat', 'LineWidth',5,</pre>
		'CDataMapping','scaled')
Each unique vertex has a single, unique color, indexed from the whole colormap. Faces each have a single, unique color, but edges may have 'flat' or 'interp' color.	 FaceColor: 'flat' FaceVertexCData: k-by-1 matrix of index values Color source: colormap CDataMapping: 'direct' 'scaled' is the default value when you input 	<pre>clear cdata set(gca,'CLim',[0 40]) cdata = [15 30 25 2 60 12 23 40 13 26 24]'; set(p,'FaceColor','flat', 'FaceVertexCData',cdata, 'CDataMapping','direct', 'EdgeColor','flat',</pre>
	CData values. If you want to change the axes CLim property, but want your patch object to index the entire colormap, use 'CDataMapping','direct'.	'LineWidth',5)

Desired Look	Parameter Values	Sample Code
Each unique vertex has a single, unique color, determined by truecolor value input. Faces each have a single, unique color, but edges may have 'flat' or 'interp' color.	 FaceColor: 'flat' FaceVertexCData: k-by-3 matrix of truecolor values, from 0 to 1 Color source: truecolor CDataMapping: 'direct' or 'scaled'. 	clear cdata cdata = [0 0 1; 0 1 0; 0 1 1; 1 0 0; 1 0 1; 1 1 0; 0 0 0;
	'scaled' is the default value, but neither affects the outcome.	0.2 0.2 0.2; 0.4 0.4 0.4; 0.6 0.6 0.6; 0.8 0.8 0.8]; set(p,'FaceColor','flat', 'FaceVertexCData',cdata, 'EdgeColor','interp', 'LineWidth',5)
Each unique vertex has a single, unique color, indexed from a selected section of the colormap. Edges may have 'flat' or 'interp' color.	 FaceColor: 'interp' FaceVertexCData: k-by-1 matrix of index values Color source: A selected portion of the colormap CDataMapping: 'scaled' 	<pre>clear cdata set(gca,'CLim',[0 40]) cdata = [15 30 25 2 60 12 23 40 13 26 24]'; set(p,'FaceColor','interp', 'FaceVertexCData',cdata, 'EdgeColor','flat', 'LineWidth',5 'CDataMapping','scaled')</pre>

patch

Desired Look	Parameter Values	Sample Code
Each unique vertex has a single, unique color, indexed from the whole colormap. Edges may have 'flat' or 'interp' color.	 FaceColor: 'interp' FaceVertexCData: k-by-1 matrix of index values Color source: colormap CDataMapping: 'direct' 	<pre>clear cdata set(gca,'CLim',[0 40]) cdata = [15 30 25 2 60 12 23 40 13 26 24]'; set(p,'FaceColor','interp', 'FaceVertexCData',cdata,</pre>
	<pre>'scaled' is the default value when you input CData values. If you want to change the axes CLim property, but want your patch object to index the entire colormap, use 'CDataMapping','direct'.</pre>	'CDataMapping','direct', 'EdgeColor','flat', 'LineWidth',5)
Each unique vertex has a single, unique color, determined by truecolor value input. Edges may have 'flat' or 'interp' color.	 FaceColor: 'interp' FaceVertexCData: k-by-3 matrix of truecolor values, from 0 to 1 Color source: truecolor 	clear cdata cdata = [0 0 1; 0 1 0; 0 1 1; 1 0 0;
	• CDataMapping: 'direct' or 'scaled'. 'scaled' is the default value, but neither affects the outcome.	<pre>1 0 1; 1 1 0; 0 0 0; 0.2 0.2 0.2; 0.4 0.4 0.4; 0.6 0.6 0.6; 0.8 0.8 0.8]; set(p,'FaceColor','interp', 'FaceVertexCData',cdata, 'EdgeColor','interp', 'LineWidth',5)</pre>

Specifying Face Colors Using x-, y-, and z-Coordinate Input

The following options apply to the face colors of your patch object when you specify the faces using x-, y-, and z-coordinates. To explore the options, first start with a base patch object:

For more information on the relevant properties, see FaceColor, CData, and CDataMapping.

Parameter Values	Sample Code
• FaceColor: ColorSpec	
• FaceVertexCData: [] (no	<pre>set(p,'FaceColor','r')</pre>
input)	or
• Color source: truecolor	<pre>set(p,'FaceColor',[1 0 0])</pre>
• CDataMapping: 'direct' or 'scaled'.	set(p, racecoror ,[r 0 0])
'scaled' is the default value, but neither affects the outcome.	
• FaceColor: 'flat'	
• FaceVertexCData: m-by-1 matrix of index values	clear cdata set(gca,'CLim',[0 40]) cdata = [15 30 25 2 60];
	 FaceColor: ColorSpec FaceVertexCData: [] (no input) Color source: truecolor CDataMapping: 'direct' or 'scaled'. 'scaled' is the default value, but neither affects the outcome. FaceColor: 'flat' FaceVertexCData: m-by-1

patch

Desired Look	Parameter Values	Sample Code
	 Color source: A selected portion of the colormap CDataMapping: 'scaled' 	set(p,'FaceColor','flat', 'CData',cdata 'CDataMapping','scaled')
Each face has a single, unique color, indexed from the whole colormap.	 FaceColor: 'flat' FaceVertexCData: m-by-1 matrix of index values Color source: colormap 	clear cdata set(gca,'CLim',[0 40]) cdata = [15 30 25 2 60]; set(p,'FaceColor','flat',
	• CDataMapping: 'direct' 'scaled' is the default value when you input CData values. If you want to change the axes CLim property, but want your patch object to index the entire colormap, use 'CDataMapping', 'direct'.	'CData',cdata, 'CDataMapping','direct')

Desired Look	Parameter Values	Sample Code
Each face has a single, unique color, determined by truecolor value input.	 FaceColor: 'flat' FaceVertexCData: m-by-1-by-3 matrix of truecolor values, from 0 to 1 	<pre>clear cdata cdata(:,:,1) = [0 0 1 0 0.8]; cdata(:,:,2) = [0 0 0 0 0.8]; cdata(:,:,3) = [1 1 1 0 0.8];</pre>
	 Color source: truecolor CDataMapping: 'direct' or 'scaled'. 'scaled' is the default value, but neither affects the outcome. 	set(p,'FaceColor','flat', 'CData',cdata)
Each unique vertex has a single, unique color, indexed from a selected section of the colormap. Faces each have a single, unique color, but edges may have 'flat' or 'interp' color.	 FaceColor: 'flat' FaceVertexCData: m-by-n matrix of index values Color source: A selected portion of the colormap CDataMapping: 'scaled' 	Clear cdata set(gca,'CLim',[0 40]) cdata = [15 30 25 2 60; 12 23 40 13 26; 24 8 1 65 42]; set(p,'FaceColor','flat', 'CData',cdata, 'EdgeColor','flat',
		'LineWidth',5 'CDataMapping','scaled')

patch

Desired Look	Parameter Values	Sample Code
Each unique vertex has a single, unique color, indexed from the whole colormap. Faces each have a single, unique color, but edges may have 'flat' or 'interp' color.	 FaceColor: 'flat' FaceVertexCData: m-by-n matrix of index values Color source: colormap CDataMapping: 'direct' 'scaled' is the default value when you input 	Clear cdata set(gca,'CLim',[0 40]) cdata = [15 30 25 2 60; 12 23 40 13 26; 24 8 1 65 42]; set(p,'FaceColor','flat', 'CData',cdata, 'CDataMapping','direct',
	CData values. If you want to change the axes CLim property, but want your patch object to index the entire colormap, use 'CDataMapping','direct'.	'EdgeColor','flat', 'LineWidth',5)
Each vertex has a single, unique color, determined by truecolor value input. Faces each have a single, unique color, but edges	 FaceColor: 'flat' FaceVertexCData: m-by-n-by-3 matrix of truecolor values, from 0 to 1 	clear cdata cdata(:,:,1) = [0 0 1 0 0.8; 0 0 1 0.2 0.6; 0 1 0 0.4 1];
may have 'flat' or 'interp' color.	 Color source: truecolor CDataMapping: 'direct' or 'scaled'. 	cdata(:,:,2) = [0 0 0 0 0.8; 1 1 1 0.2 0.6; 1 0 0 0.4 0];
	'scaled' is the default value, but neither affects the outcome.	<pre>cdata(:,:,3) = [1 1 1 0 0.8;</pre>

Desired Look	Parameter Values	Sample Code
Each vertex has a single, unique color, indexed from a selected section of the colormap. Edges may have 'flat' or 'interp' color.	 FaceColor: 'interp' FaceVertexCData: m-by-n matrix of index values Color source: A selected portion of the colormap CDataMapping: 'scaled' 	<pre>clear cdata set(gca,'CLim',[0 40]) cdata = [15 30 25 2 60;</pre>
Each vertex has a single, unique color, indexed from the whole colormap. Edges may have 'flat' or 'interp' color.	 FaceColor: 'interp' FaceVertexCData: m-by-n matrix of index values Color source: colormap CDataMapping: 'direct' 	clear cdata set(gca,'CLim',[0 40]) cdata = [15 30 25 2 60; 12 23 40 13 26; 24 8 1 65 42]; set(p,'FaceColor','interp',
	'scaled' is the default value when you input CData values. If you want to change the axes CLim property, but want your patch object to index the entire colormap, use 'CDataMapping','direct'.	'CData',cdata, 'CDataMapping','direct', 'EdgeColor','flat', 'LineWidth',5)
Each vertex has a single, unique color, determined by truecolor value input. Edges	 FaceColor: 'interp' FaceVertexCData: m-by-n-by-3 matrix of 	clear cdata cdata(:,:,1) = [0.8 0.1 0.2 0.9 0.3 1;

patch

Desired Look	Parameter Values	Sample Code
may have 'flat' or 'interp' color.	<pre>truecolor values, from 0 to 1 • Color source: truecolor • CDataMapping: 'direct' or 'scaled'. 'scaled' is the default value, but neither affects the outcome.</pre>	<pre>0.1 0.5 0.9; 0.9 1 0.5; 0.6 0.9 0.8]; cdata(:,:,2) =[0.1 0.6 0.7; 0.4 0.1 0.7; 0.9 0.8 0.3; 0.7 0.9 0.6; 0.9 0.6 0.1]; cdata(:,:,3) =[0.7 0.8 0.4; 0.1 0.6 0.3; 0.2 0.3 0.7; 0.0 0.9 0.7; 0.0 0.9 0.7; 0.0 0.0 0.1]; set(p,'FaceColor','interp', 'CData',cdata, 'EdgeColor','interp',</pre>

- See Also area | caxis | fill | fill3 | isosurface | surface | FaceColor | CData | CDataMapping | FaceVertexCData | Patch Properties
- **Tutorials** "Creating 3-D Models with Patches"

Patch Properties

Purpose	Patch properties
Creating Patch Objects	Use patch to create patch objects.
Modifying Properties	 You can set and query graphics object properties in two ways: "The Property Editor" is an interactive tool that enables you to see and change object property values. The set and get commands enable you to set and query the values of properties. To change the default values of properties, see "Setting Default Property Values". See "Core Graphics Objects" for general information about this type of object.
Patch Property Descriptions	 This section lists property names along with the type of values each accepts. Curly braces {} enclose default values. AlphaDataMapping none {scaled} direct Transparency mapping method. This property determines how the MATLAB software interprets indexed alpha data. This property can be any of the following: none — The transparency values of FaceVertexAlphaData are between 0 and 1 or are clamped to this range. scaled — Transform the FaceVertexAlphaData to span the portion of the alphamap indicated by the axes ALim property, linearly mapping data values to alpha values. (scaled is the default)

• direct — Use the FaceVertexAlphaData as indices directly into the alphamap. When not scaled, the data are usually integer values ranging from 1 to length(alphamap). MATLAB maps values less than 1 to the first alpha value in the alphamap, and values greater than length(alphamap) to the last alpha value in the alphamap. Values with a decimal portion are fixed to the nearest lower integer. If FaceVertexAlphaData is an array of uint8 integers, then the indexing begins at 0 (i.e., MATLAB maps a value of 0 to the first alpha value in the alphamap).

AmbientStrength

scalar ≥ 0 and ≤ 1

Strength of ambient light. This property sets the strength of the ambient light, which is a nondirectional light source that illuminates the entire scene. You must have at least one visible light object in the axes for the ambient light to be visible. The axes AmbientColor property sets the color of the ambient light, which is therefore the same on all objects in the axes.

You can also set the strength of the diffuse and specular contribution of light objects. See the DiffuseStrength and SpecularStrength properties.

Annotation

hg.Annotation object Read Only

Control the display of patch objects in legends. The Annotation property enables you to specify whether this patch object is represented in a figure legend.

Querying the Annotation property returns the handle of an hg.Annotation object. The hg.Annotation object has a property called LegendInformation, which contains an hg.LegendEntry object.

Once you have obtained the hg.LegendEntry object, you can set its IconDisplayStyle property to control whether the patch object is displayed in a figure legend:

IconDisplayStyle Value	Purpose
on	Represent this patch object in a legend (default)
off	Do not include this patch object in a legend
children	Same as on because patch objects do not have children

Setting the IconDisplayStyle property

These commands set the IconDisplayStyle of a graphics object with handle hobj to off:

```
hAnnotation = get(hobj, 'Annotation');
hLegendEntry = get(hAnnotation', 'LegendInformation');
set(hLegendEntry, 'IconDisplayStyle', 'off')
```

Using the IconDisplayStyle property

See "Controlling Legends" for more information and examples.

Selecting which objects to display in legend

Some graphics functions create multiple objects. For example, contour3 uses patch objects to create a 3D contour graph. You can use the Annotation property set select a subset of the objects for display in the legend.

```
[X,Y] = meshgrid(-2:.1:2);
[Cm hC] = contour3(X.*exp(-X.^2-Y.^2));
hA = get(hC, 'Annotation');
hLL = get([hA{:}], 'LegendInformation');
```

```
% Set the IconDisplayStyle property to display
% the first, fifth, and ninth patch in the legend
set([hLL{:}],{'IconDisplayStyle'},...
{'on','off','off','off','off','off','off','on'}')
% Assign DisplayNames for the three patch
that are displayed in the legend
set(hC([1,5,9]),{'DisplayName'},{'bottom','middle','top'}')
legend show
```

BackFaceLighting

unlit | lit | {reverselit}

Face lighting control. This property determines how faces are lit when their vertex normals point away from the camera:

- unlit Face is not lit.
- lit Face is lit in normal way.
- reverselit Face is lit as if the vertex pointed towards the camera.

This property is useful for discriminating between the internal and external surfaces of an object. See the Using MATLAB Graphics manual for an example.

BeingDeleted

on | {off} Read Only

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property) It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions may not need to perform actions on objects that are going to be deleted, and therefore, can check the object's **BeingDeleted** property before acting.

BusyAction

cancel | {queue}

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callback routines. If there is a callback routine executing, callback routines invoked subsequently always attempt to interrupt it. If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are

- cancel Discard the event that attempted to execute a second callback routine.
- queue Queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Button press callback routine. A callback routine that executes whenever you press a mouse button while the pointer is over the patch object.

See the figure's SelectionType property to determine if modifier keys were also pressed.


Set this property to a function handle that references the callback. You can also use a string that is a valid MATLAB expression or the name of a MATLAB file. The expressions execute in the MATLAB workspace. See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

CData


scalar, vector, or matrix

Patch colors. This property specifies the color of the patch. You can specify color for each vertex, each face, or a single color for the entire patch. The way MATLAB interprets CData depends on the type of data supplied. The data can be numeric values that are scaled to map linearly into the current colormap, integer values that are used directly as indices into the current colormap, or arrays of RGB values. RGB values are not mapped into the current colors, but interpreted as the colors defined. On true color systems, MATLAB uses the actual colors defined by the RGB triples.

The following two diagrams illustrate the dimensions of CData with respect to the coordinate data arrays, XData, YData, and ZData. The first diagram illustrates the use of indexed color.



The second diagram illustrates the use of true color. True color requires m-by-n-by-3 arrays to define red, green, and blue components for each color.



Note that if $\ensuremath{\mathsf{CData}}$ contains NaNs, MATLAB does not color the faces.

See also the Faces, Vertices, and FaceVertexCData properties for an alternative method of patch definition.

CDataMapping

{scaled} | direct

Direct or scaled color mapping. This property determines how MATLAB interprets indexed color data used to color the patch. (If you use true color specification for CData or FaceVertexCData, this property has no effect.)

• scaled — Transform the color data to span the portion of the colormap indicated by the axes CLim property, linearly

mapping data values to colors. See the caxis command for more information on this mapping.

• direct — Use the color data as indices directly into the colormap. When not scaled, the data are usually integer values ranging from 1 to length(colormap). MATLAB maps values less than 1 to the first color in the colormap, and values greater than length(colormap) to the last color in the colormap. Values with a decimal portion are fixed to the nearest lower integer.

Children

matrix of handles

Always the empty matrix; patch objects have no children.

Clipping

{on} | off

Clipping to axes rectangle. When Clipping is on, MATLAB does not display any portion of the patch outside the axes rectangle.

CreateFcn

string or function handle

Callback routine executed during object creation. This property defines a callback routine that executes when MATLAB creates a patch object. You must define this property as a default value for patches or in a call to the patch function that creates a new object.

For example, the following statement creates a patch (assuming x, y, z, and c are defined), and executes the function referenced by the function handle @myCreateFcn.

patch(x,y,z,c,'CreateFcn',@myCreateFcn)

MATLAB executes the create function after setting all properties for the patch created. Setting this property on an existing patch object has no effect. The handle of the object whose CreateFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DeleteFcn

string or function handle

Delete patch callback routine. A callback routine that executes when you delete the patch object (for example, when you issue a delete command or clear the axes (cla) or figure (clf) containing the patch). MATLAB executes the routine before deleting the object's properties so these values are available to the callback routine.

The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

See Function Handle Callbacks for information on how to use function handles to define the callback function.

DiffuseStrength

scalar ≥ 0 and ≤ 1

Intensity of diffuse light. This property sets the intensity of the diffuse component of the light falling on the patch. Diffuse light comes from light objects in the axes.

You can also set the intensity of the ambient and specular components of the light on the patch object. See the AmbientStrength and SpecularStrength properties.

DisplayName

string (default is empty string)

String used by legend for this patch object. The legend function uses the string defined by the DisplayName property to label this patch object in the legend.

- If you specify string arguments with the legend function, DisplayName is set to this patch object's corresponding string and that string is used for the legend.
- If DisplayName is empty, legend creates a string of the form, ['data' n], where n is the number assigned to the object based on its location in the list of legend entries. However, legend does not set DisplayName to this string.
- If you edit the string directly in an existing legend, DisplayName is set to the edited string.
- If you specify a string for the DisplayName property and create the legend using the figure toolbar, then MATLAB uses the string defined by DisplayName.
- To add programmatically a legend that uses the DisplayName string, call legend with the toggle or show option.

See "Controlling Legends" for more examples.

EdgeAlpha

{scalar = 1} | flat | interp

Transparency of the edges of patch faces. This property can be any of the following:

- scalar A single non-NaN scalar value between 0 and 1 that controls the transparency of all the edges of the object.
 1 (the default) means fully opaque and 0 means completely transparent.
- flat The alpha data (FaceVertexAlphaData) of each vertex controls the transparency of the edge that follows it.

• interp — Linear interpolation of the alpha data (FaceVertexAlphaData) at each vertex determines the transparency of the edge.


Note that you cannot specify flat or interp EdgeAlpha without first setting FaceVertexAlphaData to a matrix containing one alpha value per face (flat) or one alpha value per vertex (interp).

EdgeColor

{ColorSpec} | none | flat | interp

Color of the patch edge. This property determines how MATLAB colors the edges of the individual faces that make up the patch.

- ColorSpec A three-element RGB vector or one of the MATLAB predefined names, specifying a single color for edges. The default edge color is black. See ColorSpec for more information on specifying color.
- none Edges are not drawn.
- flat The color of each vertex controls the color of the edge that follows it. This means flat edge coloring is dependent on the order in which you specify the vertices:



• interp — Linear interpolation of the CData or FaceVertexCData values at the vertices determines the edge color.

EdgeLighting

{none} | flat | gouraud | phong

Algorithm used for lighting calculations. This property selects the algorithm used to calculate the effect of light objects on patch edges. Choices are

- none Lights do not affect the edges of this object.
- flat The effect of light objects is uniform across each edge of the patch.
- gouraud The effect of light objects is calculated at the vertices and then linearly interpolated across the edge lines.
- phong The effect of light objects is determined by interpolating the vertex normals across each edge line and calculating the reflectance at each pixel. Phong lighting generally produces better results than Gouraud lighting, but takes longer to render.

EraseMode

{normal} | none | xor | background

Erase mode. This property controls the technique MATLAB uses to draw and erase patch objects. Alternative erase modes are useful in creating animated sequences, where control of the way individual objects redraw is necessary to improve performance and obtain the desired effect.

- normal Redraw the affected region of the display, performing the three-dimensional analysis necessary to ensure that all objects are rendered correctly. This mode produces the most accurate picture, but is the slowest. The other modes are faster, but do not perform a complete redraw and are therefore less accurate.
- none Do not erase the patch when it is moved or destroyed. While the object is still visible on the screen after erasing with EraseMode none, you cannot print it because MATLAB stores no information about its former location.
- xor Draw and erase the patch by performing an exclusive OR (XOR) with each pixel index of the screen behind it. Erasing

the patch does not damage the color of the objects behind it. However, patch color depends on the color of the screen behind it and is correctly colored only when over the axes background Color, or the figure background Color if the axes Color is set to none.

• background — Erase the patch by drawing it in the axes background Color, or the figure background Color if the axes Color is set to none. This damages objects that are behind the erased patch, but the patch is always properly colored.

Printing with Nonnormal Erase Modes

MATLAB always prints figures as if the EraseMode of all objects is normal. This means graphics objects created with EraseMode set to none, xor, or background can look different on screen than on paper. On screen, MATLAB may mathematically combine layers of colors (for example, perform an XOR of a pixel color with that of the pixel behind it) and ignore three-dimensional sorting to obtain greater rendering speed. However, these techniques are not applied to the printed output.

You can use the MATLAB getframe command or other screen capture application to create an image of a figure containing nonnormal mode objects.

FaceAlpha

{scalar = 1} | flat | interp

Transparency of the patch face. This property can be any of the following:

• A scalar — A single non-NaN value between 0 and 1 that controls the transparency of all the faces of the object. 1 (the default) means fully opaque and 0 means completely transparent (invisible).

- flat The values of the alpha data (FaceVertexAlphaData) determine the transparency for each face. The alpha data at the first vertex determines the transparency of the entire face.
- interp Bilinear interpolation of the alpha data (FaceVertexAlphaData) at each vertex determines the transparency of each face.

Note that you cannot specify flat or interp FaceAlpha without first setting FaceVertexAlphaData to a matrix containing one alpha value per face (flat) or one alpha value per vertex (interp).

FaceColor

{ColorSpec} | none | flat | interp

Color of the patch face. This property can be any of the following:

- ColorSpec A three-element RGB vector or one of the MATLAB predefined names, specifying a single color for faces. See ColorSpec for more information on specifying color.
- none Do not draw faces. Note that edges are drawn independently of faces.
- flat The CData or FaceVertexCData property must contain one value per face and determines the color for each face in the patch. The color data at the first vertex determines the color of the entire face.
- interp Bilinear interpolation of the color at each vertex determines the coloring of each face. The CData or FaceVertexCData property must contain one value per vertex.

FaceLighting

{none} | flat | gouraud | phong

Algorithm used for lighting calculations. This property selects the algorithm used to calculate the effect of light objects on patch faces. Choices are

• none — Lights do not affect the faces of this object.

- flat The effect of light objects is uniform across the faces of the patch. Select this choice to view faceted objects.
- gouraud The effect of light objects is calculated at the vertices and then linearly interpolated across the faces. Select this choice to view curved surfaces.
- phong The effect of light objects is determined by interpolating the vertex normals across each face and calculating the reflectance at each pixel. Select this choice to view curved surfaces. Phong lighting generally produces better results than Gouraud lighting, but takes longer to render.


Faces

m-by-n matrix

Vertex connection defining each face. This property is the connection matrix specifying which vertices in the Vertices property are connected. The Faces matrix defines m faces with up to n vertices each. Each row designates the connections for a single face, and the number of elements in that row that are not NaN defines the number of vertices for that face.

The Faces and Vertices properties provide an alternative way to specify a patch that can be more efficient than using x, y, and z coordinates in most cases. For example, consider the following patch. It is composed of eight triangular faces defined by nine vertices.

Faces property Vertices property



The corresponding Faces and Vertices properties are shown to the right of the patch. Note how some faces share vertices with other faces. For example, the fifth vertex (V5) is used six times, once each by faces one, two, and three and six, seven, and eight. Without sharing vertices, this same patch requires 24 vertex definitions.

FaceVertexAlphaData

m-by-1 matrix

Face and vertex transparency data. The FaceVertexAlphaData property specifies the transparency of patches that have been defined by the Faces and Vertices properties. The interpretation of the values specified for FaceVertexAlphaData depends on the dimensions of the data.

FaceVertexAlphaData can be one of the following:

- A single value, which applies the same transparency to the entire patch. The FaceAlpha property must be set to flat.
- An m-by-1 matrix (where m is the number of rows in the Faces property), which specifies one transparency value per face. The FaceAlpha property must be set to flat.

• An m-by-1 matrix (where m is the number of rows in the Vertices property), which specifies one transparency value per vertex. The FaceAlpha property must be set to interp.

The AlphaDataMapping property determines how MATLAB interprets the FaceVertexAlphaData property values.

FaceVertexCData

matrix

Face and vertex colors. The FaceVertexCData property specifies the color of patches defined by the Faces and Vertices properties. You must also set the values of the FaceColor, EdgeColor, MarkerFaceColor, or MarkerEdgeColor appropriately. The interpretation of the values specified for FaceVertexCData depends on the dimensions of the data.


For indexed colors, FaceVertexCData can be

- A single value, which applies a single color to the entire patch
- An *n*-by-1 matrix, where *n* is the number of rows in the Faces property, which specifies one color per face
- An *n*-by-1 matrix, where *n* is the number of rows in the Vertices property, which specifies one color per vertex

For true colors, FaceVertexCData can be

- A 1-by-3 matrix, which applies a single color to the entire patch
- An *n*-by-3 matrix, where *n* is the number of rows in the Faces property, which specifies one color per face
- An *n*-by-3 matrix, where *n* is the number of rows in the Vertices property, which specifies one color per vertex

The following diagram illustrates the various forms of the FaceVertexCData property for a patch having eight faces and nine vertices. The CDataMapping property determines how



MATLAB interprets the FaceVertexCData property when you specify indexed colors.

```
HandleVisibility
{on} | callback | off
```

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally drawing into or deleting a figure that contains only user interface devices (such as a dialog box).

Handles are always visible when HandleVisibility is on.

Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.

Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close.

When a handle's visibility is restricted using callback or off, the object's handle does not appear in its parent's Children property, figures do not appear in the root's CurrentFigure property, objects do not appear in the root's CallbackObject property or in the figure's CurrentObject property, and axes do not appear in their parent's CurrentAxes property.

You can set the root ShowHiddenHandles property to on to make all handles visible regardless of their HandleVisibility settings (this does not affect the values of the HandleVisibility properties).

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

HitTest

{on} | off

Selectable by mouse click. HitTest determines if the patch can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click on the patch. If HitTest is off, clicking the patch selects the object below it (which may be the axes containing it).

Interruptible

 $\{on\} \mid off$

Callback routine interruption mode. The Interruptible property controls whether a patch callback routine can be interrupted by subsequently invoked callback routines. Only callback routines defined for the ButtonDownFcn are affected by the Interruptible property. MATLAB checks for events that can interrupt a callback routine only when it encounters a drawnow, figure, getframe, or pause command in the routine. See the BusyAction property for related information.

LineStyle

{-} | -- | : | -. | none

Edge linestyle. This property specifies the line style of the patch edges. The following table lists the available line styles.

Symbol	Line Style
-	Solid line (default)
	Dashed line
:	Dotted line
	Dash-dot line
none	No line

You can use LineStyle none when you want to place a marker at each point but do not want the points connected with a line (see the Marker property).

LineWidth scalar *Edge line width*. The width, in points, of the patch edges (1 point = $\frac{1}{72}$ inch). The default LineWidth is 0.5 points.

Marker

character (see table)

Marker symbol. The Marker property specifies marks that locate vertices. You can set values for the Marker property independently from the LineStyle property. The following tables lists the available markers.

Marker Specifier	Description
+	Plus sign
0	Circle
*	Asterisk
	Point
х	Cross
S	Square
d	Diamond
^	Upward-pointing triangle
V	Downward-pointing triangle
>	Right-pointing triangle
<	Left-pointing triangle
р	Five-pointed star (pentagram)
h	Six-pointed star (hexagram)
none	No marker (default)

MarkerEdgeColor

ColorSpec | none | {auto} | flat

Marker edge color. The color of the marker or the edge color for filled markers (circle, square, diamond, pentagram, hexagram, and the four triangles).

- ColorSpec Defines the color to use.
- none Specifies no color, which makes nonfilled markers invisible.
- auto Sets MarkerEdgeColor to the same color as the EdgeColor property.
- flat The color of each vertex controls the color of the marker that denotes it.

MarkerFaceColor

ColorSpec | {none} | auto | flat

Marker face color. The fill color for markers that are closed shapes (circle, square, diamond, pentagram, hexagram, and the four triangles).

- ColorSpec Defines the color to use.
- none Makes the interior of the marker transparent, allowing the background to show through.
- auto Sets the fill color to the axes color, or the figure color, if the axes Color property is set to none.
- flat The color of each vertex controls the color of the marker that denotes it.

MarkerSize

size in points

Marker size. A scalar specifying the size of the marker, in points. The default value for MarkerSize is 6 points (1 point = $1/_{72}$ inch). Note that MATLAB draws the point marker at 1/3 of the specified size.

NormalMode

{auto} | manual

MATLAB generated or user-specified normal vectors. When this property is auto, MATLAB calculates vertex normals based on the coordinate data. If you specify your own vertex normals, MATLAB sets this property to manual and does not generate its own data. See also the VertexNormals property.

Parent

handle of axes, hggroup, or hgtransform

Parent of patch object. This property contains the handle of the patch object's parent. The parent of a patch object is the axes, hggroup, or hgtransform object that contains it.

See "Objects That Can Contain Other Objects" for more information on parenting graphics objects.

Selected

on | {off}

Is object selected? When this property is on, MATLAB displays selection handles or a dashed box (depending on the number of faces) if the SelectionHighlight property is also on. You can, for example, define the ButtonDownFcn to set this property, allowing users to select the object with the mouse.

SelectionHighlight

{on} | off

Objects are highlighted when selected. When the Selected property is on, MATLAB indicates the selected state by

- Drawing handles at each vertex for a single-faced patch
- Drawing a dashed bounding box for a multifaced patch

When SelectionHighlight is off, MATLAB does not draw the handles.

```
SpecularColorReflectance
scalar in the range 0 to 1
```

Color of specularly reflected light. When this property is 0, the color of the specularly reflected light depends on both the color of the object from which it reflects and the color of the light source. When set to 1, the color of the specularly reflected light depends only on the color of the light source (i.e., the light object Color property). The proportions vary linearly for values in between.

SpecularExponent

```
scalar \geq 1
```

Harshness of specular reflection. This property controls the size of the specular spot. Most materials have exponents in the range of 5 to 20.

SpecularStrength

scalar ≥ 0 and ≤ 1

Intensity of specular light. This property sets the intensity of the specular component of the light falling on the patch. Specular light comes from light objects in the axes.

You can also set the intensity of the ambient and diffuse components of the light on the patch object. See the AmbientStrength and DiffuseStrength properties.

Тад

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when you are constructing interactive graphics programs that would otherwise need to define object handles as

global variables or pass them as arguments between callback routines.

For example, suppose you use patch objects to create borders for a group of uicontrol objects and want to change the color of the borders in a uicontrol's callback routine. You can specify a Tag with the patch definition

```
patch(X,Y,'k','Tag','PatchBorder')
```

Then use findobj in the uicontrol's callback routine to obtain the handle of the patch and set its FaceColor property.

```
set(findobj('Tag', 'PatchBorder'), 'FaceColor', 'w')
```

Туре

string (read only)

Class of the graphics object. For patch objects, Type is always the string 'patch'.

UIContextMenu

handle of a uicontextmenu object

Associate a context menu with the patch. Assign this property the handle of a uicontextmenu object created in the same figure as the patch. Use the uicontextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click over the patch.

UserData

matrix

User-specified data. Any matrix you want to associate with the patch object. MATLAB does not use this data, but you can access it using set and get.

VertexNormals

matrix

Surface normal vectors. This property contains the vertex normals for the patch. MATLAB generates this data to perform lighting calculations. You can supply your own vertex normal data, even if it does not match the coordinate data. This can be useful to produce interesting lighting effects.

Vertices

matrix

Vertex coordinates. A matrix containing the *x*-, *y*-, *z*-coordinates for each vertex. See the Faces property for more information.

Visible

{on} | off

Patch object visibility. By default, all patches are visible. When set to off, the patch is not visible, but still exists, and you can query and set its properties.

XData

vector or matrix

X-coordinates. The *x*-coordinates of the patch vertices. If XData is a matrix, each column represents the *x*-coordinates of a single face of the patch. In this case, XData, YData, and ZData must have the same dimensions.

YData

vector or matrix

Y-coordinates. The *y*-coordinates of the patch vertices. If YData is a matrix, each column represents the *y*-coordinates of a single face of the patch. In this case, XData, YData, and ZData must have the same dimensions.

ZData

vector or matrix

Z-coordinates. The z-coordinates of the patch vertices. If ZData is a matrix, each column represents the z-coordinates of a single face of the patch. In this case, XData, YData, and ZData must have the same dimensions.

See Also

patch

path

Purpose	View or change search path
GUI Alternatives	As an alternative to the path function, use the Set Path dialog box.
Syntax	<pre>path path('newpath') path(path,'newpath') path('newpath',path) p = path</pre>
Description	path displays the MATLAB search path, which is stored in pathdef.m. path('newpath') changes the search path to newpath, where newpath is a string array of folders.
	<pre>path(path, 'newpath') adds the newpath folder to the end of the search path. If newpath is already on the search path, then path(path, 'newpath') moves newpath to the end of the search path.</pre>
	<pre>path('newpath',path) adds the newpath folder to the top of the search path. If newpath is already on the search path, then path('newpath', path) moves newpath to the top of the search path. To add multiple folders in one statement, instead use addpath.</pre>
	p = path returns the search path to string variable p .
Examples	Display the search path: path
	MATLAB returns, for example MATLABPATH H:\My Documents\MATLAB C:\Program Files\MATLAB\R200nn\toolbox\matlab\general C:\Program Files\MATLAB\R200nn\toolbox\matlab\ops C:\Program Files\MATLAB\R200nn\toolbox\matlab\lang

```
C:\Program Files\MATLAB\R200nn\toolbox\matlab\elmat
C:\Program Files\MATLAB\R200nn\toolbox\matlab\elfun
...
```

R200nn represents the folder for the MATLAB release, for example, R2009b.

Add a new folder to the search path on Microsoft Windows platforms:

```
path(path,'c:/tools/goodstuff')
```

```
      Add a new folder to the search path on UNIX<sup>13</sup> platforms:

      path(path, '/home/tools/goodstuff')

      Temporarily add the folder my_files to the search path, run my_function in my_files, then restore the previous search path:

      p = path

      path('my_files')

      my_function

      path(p)

      See Also

      addpath, cd, dir, genpath, matlabroot, pathsep, pathtool, rehash, restoredefaultpath, rmpath, savepath, startup, userpath, what

      Topics in the User Guide:

      • "Using the MATLAB Search Path"

      • "Making Files and Folders Accessible to MATLAB"
```

13. UNIX is a registered trademark of The Open Group in the United States and other countries.

Purpose Save current search path to pathdef.m file	
---	--

- Syntax path2rc
- **Description** path2rc runs savepath. The savepath function is replacing path2rc. Use savepath instead of path2rc and replace instances of path2rc with savepath.

pathsep

Purpose	Search path separator for current platform
Syntax	c = pathsep
Description	c = pathsep returns the search path separator character for this platform. The search path separator is the character that separates path names in the pathdef.m file, as returned by the path function. The character is a semicolon (;). For versions of MATLAB software earlier than version 7.7 (R2008b), the character on UNIX ¹⁴ platforms was a colon (:). Use pathsep to work programmatically with the content of the search path file.
See Also	fileparts, filesep, fullfile, path "Using the MATLAB Search Path"
	UNIX is a registered trademark of The Open Group in the United States and ther countries.

pathtool

Purpose	Open Set Path dialog box to view and change search path
GUI Alternatives	As an alternative to the pathtool function, select File > Set Path in the MATLAB desktop.
Syntax	pathtool
Description	pathtool opens the Set Path dialog box, a graphical user interface you use to view and modify the MATLAB search path.

📣 Set Path

All changes take effect immediately.

	MATLAB search path:	
Add Folder	H:\Documents\MATLAB	
Add with Subfolders	C:\Program Files\MATLAB\R2009b\toolbox\matlab\general	
	🛅 C:\Program Files\MATLAB\R2009b\toolbox\matlab\lang	
Move to Top	C:\Program Files\MATLAB\R2009b\toolbox\matlab\elmat C:\Program Files\MATLAB\R2009b\toolbox\matlab\randfun	
Move Up	🛅 C:\Program Files\MATLAB\R2009b\toolbox\matlab\elfun	
	C:\Program Files\MATLAB\R2009b\toolbox\matlab\specfun	
Move Down	🛅 C:\Program Files\MATLAB\R2009b\toolbox\matlab\matfun	
Move to Bottom	🛅 C:\Program Files\MATLAB\R2009b\toolbox\matlab\datafun	
	🛅 C:\Program Files\MATLAB\R2009b\toolbox\matlab\polyfun	
	🗀 C:\Program Files\MATLAB\R2009b\toolbox\matlab\funfun	
Demons	🛅 C:\Program Files\MATLAB\R2009b\toolbox\matlab\sparfun	
Remove	🛅 C:\Program Files\MATLAB\R2009b\toolbox\matlab\scribe	-
Save Close	Revert Default b	lp

pathtool

See Also addpath, cd, dir, genpath, matlabroot, path, pathsep, rehash, restoredefaultpath, rmpath, savepath, startup, what

"Using the MATLAB Search Path"

Purpose	Halt execution temporarily
Syntax	pause pause(n)
	pause on
	pause off
	pause query
	state = pause('query')
	oldstate = pause(newstate)
Description	pause, by itself, causes the currently executing function to stop and wait for you to press any key before continuing. Pausing must be enabled for this to take effect. (See pause on below) pause without arguments

this to take effect. (See pause on, below). pause without arguments also blocks execution of Simulink models, but not repainting of them. pause(n) pauses execution for n seconds before continuing, where n can be any poppositive real number. The resolution of the clock is platform

be any nonnegative real number. The resolution of the clock is platform specific. A fractional pause of 0.01 seconds should be supported on most platforms. Pausing must be enabled for this to take effect.

Typing pause(inf) puts you into an infinite loop. To return to the MATLAB prompt, type **Ctrl+C**.

pause on enables the pausing of MATLAB execution via the pause and pause(n) commands. Pausing remains enabled until you enter pause off in your function or at the command line.

pause off disables the pausing of MATLAB execution via the pause and pause(n) commands. This allows normally interactive scripts to run unattended. Pausing remains disabled until you enter pause on in your function or at the command line, or start a new MATLAB session.

pause query displays 'on' if pausing is currently enabled. Otherwise, it displays 'off'.

state = pause('query') returns 'on' in character array state if
pausing is currently enabled. Otherwise, the value of state is 'off'.

oldstate = pause(newstate), enables or disables pausing, depending
on the 'on' or 'off' value in newstate, and returns the former setting
(also either 'on' or 'off') in character array oldstate.

Remarks While MATLAB is paused, the following continue to execute:

- Repainting of figure windows, Simulink block diagrams, and Java windows
- HG callbacks from figure windows
- Event handling from Java windows

See Also keyboard, input, drawnow

Purpose	Set or query plot box aspect ratio
Syntax	<pre>pbaspect pbaspect([aspect_ratio]) pbaspect('mode') pbaspect('auto') pbaspect('manual') pbaspect(axes_handle,)</pre>
Description	The plot box aspect ratio determines the relative size of the x -, y -, and z -axes.
	pbaspect with no arguments returns the plot box aspect ratio of the current axes.
	<pre>pbaspect([aspect_ratio]) sets the plot box aspect ratio in the current axes to the specified value. Specify the aspect ratio as three relative values representing the ratio of the x-, y-, and z-axes size. For example, a value of [1 1 1] (the default) means the plot box is a cube (although with stretch-to-fill enabled, it may not appear as a cube). See Remarks.</pre>
	<pre>pbaspect('mode') returns the current value of the plot box aspect ratio mode, which can be either auto (the default) or manual. See Remarks.</pre>
	<pre>pbaspect('auto') sets the plot box aspect ratio mode to auto.</pre>
	<pre>pbaspect('manual') sets the plot box aspect ratio mode to manual.</pre>
	<pre>pbaspect(axes_handle,) performs the set or query on the axes identified by the first argument, axes_handle. If you do not specify an axes handle, pbaspect operates on the current axes.</pre>
Remarks	pbaspect sets or queries values of the axes object PlotBoxAspectRatio and PlotBoxAspectRatioMode properties.
	When the plot box aspect ratio mode is auto, the MATLAB software sets the ratio to [1 1 1], but may change it to accommodate manual settings of the data aspect ratio, camera view angle, or axis limits. See the axes DataAspectRatio property for a table listing the interactions between various properties.

Setting a value for the plot box aspect ratio or setting the plot box aspect ratio mode to manual disables the MATLAB stretch-to-fill feature (stretching of the axes to fit the window). This means setting the plot box aspect ratio to its current value,


pbaspect(pbaspect)

can cause a change in the way the graphs look. See the Remarks section of the axes reference description, "Axes Aspect Ratio Properties" in the 3-D Visualization manual, and "Setting Aspect Ratio" in the MATLAB Graphics manual for a discussion of stretch-to-fill.

Examples The following surface plot of the function $z = xe^{(-x^2 - y^2)}$ is useful to illustrate the plot box aspect ratio. First plot the function over the range $-2 \le x \le 2, -2 \le y \le 2$,

```
[x,y] = meshgrid([-2:.2:2]);
z = x.*exp(-x.^2 - y.^2);
surf(x,y,z)
```

pbaspect



Querying the plot box aspect ratio shows that the plot box is square.

```
pbaspect
ans =
1 1 1
```


It is also interesting to look at the data aspect ratio selected by MATLAB.

daspect ans = 4 4 1

To illustrate the interaction between the plot box and data aspect ratios, set the data aspect ratio to $[1 \ 1 \ 1]$ and again query the plot box aspect ratio.


daspect([1 1 1])

pbaspect



The plot box aspect ratio has changed to accommodate the specified data aspect ratio. Now suppose you want the plot box aspect ratio to be $[1 \ 1 \ 1]$ as well.

```
pbaspect([1 1 1])
```




Notice how MATLAB changed the axes limits because of the constraints introduced by specifying both the plot box and data aspect ratios.

You can also use pbaspect to disable stretch-to-fill. For example, displaying two subplots in one figure can give surface plots a squashed appearance. Disabling stretch-to-fill,

```
upper_plot = subplot(211);
surf(x,y,z)
lower_plot = subplot(212);
surf(x,y,z)
pbaspect(upper_plot,'manual')
```

pbaspect



See Also axis, daspect, xlim, ylim, zlim

The axes properties DataAspectRatio, PlotBoxAspectRatio, XLim, YLim, ZLim

Setting Aspect Ratio in the MATLAB Graphics manual

Axes Aspect Ratio Properties in the 3-D Visualization manual

Purpose	Preconditioned conjugate gradients method
Syntax (1997)	<pre>x = pcg(A,b) pcg(A,b,tol) pcg(A,b,tol,maxit) pcg(A,b,tol,maxit,M) pcg(A,b,tol,maxit,M1,M2) pcg(A,b,tol,maxit,M1,M2,x0) [x,flag] = pcg(A,b,) [x,flag,relres] = pcg(A,b,) [x,flag,relres,iter] = pcg(A,b,) [x,flag,relres,iter,resvec] = pcg(A,b,)</pre>
Description	 x = pcg(A,b) attempts to solve the system of linear equations A*x=b for x. The n-by-n coefficient matrix A must be symmetric and positive definite, and should also be large and sparse. The column vector b must have length n. A can be a function handle afun such that afun(x) returns A*x. See Function Handles in the MATLAB Programming documentation for more information. "Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide additional parameters to the function afun, as well as the preconditioner function mfun described below, if necessary.
	If pcg converges, a message to that effect is displayed. If pcg fails to converge after the maximum number of iterations or halts for any reason, a warning message is printed displaying the relative residual norm(b-A*x)/norm(b) and the iteration number at which the method stopped or failed. pcg(A,b,tol) specifies the tolerance of the method. If tol is [], then pcg uses the default, 1e-6.
	<pre>pcg(A,b,tol,maxit) specifies the maximum number of iterations. If maxit is [], then pcg uses the default, min(n,20).</pre>
	pcg(A,b,tol,maxit,M) and $pcg(A,b,tol,maxit,M1,M2)$ use symmetric positive definite preconditioner M or M = M1*M2 and

effectively solve the system inv(M)*A*x = inv(M)*b for x. If M is [] then pcg applies no preconditioner. M can be a function handle mfun such that mfun(x) returns $M \setminus x$.

pcg(A,b,tol,maxit,M1,M2,x0) specifies the initial guess. If x0 is [], then pcg uses the default, an all-zero vector.

Flag	Convergence
0	<pre>pcg converged to the desired tolerance tol within maxit iterations.</pre>
1	pcg iterated maxit times but did not converge.
2	Preconditioner M was ill-conditioned.
3	pcg stagnated. (Two consecutive iterates were the same.)
4	One of the scalar quantities calculated during pcg became too small or too large to continue computing.

[x,flag] = pcg(A,b,...) also returns a convergence flag.

Whenever flag is not 0, the solution x returned is that with minimal norm residual computed over all the iterations. No messages are displayed if the flag output is specified.

[x,flag,relres] = pcg(A,b,...) also returns the relative residual norm(b-A*x)/norm(b). If flag is 0, relres <= tol.</pre>

[x,flag,relres,iter] = pcg(A,b,...) also returns the iteration
number at which x was computed, where 0 <= iter <= maxit.</pre>

[x,flag,relres,iter,resvec] = pcg(A,b,...) also returns a vector of the residual norms at each iteration including norm(b-A*x0).

Examples Example 1

```
n1 = 21;
A = gallery('moler',n1);
b1 = A*ones(n1,1);
tol = 1e-6;
```

```
maxit = 15;
M = diag([10:-1:1 1 1:10]);
[x1,flag1,rr1,iter1,rv1] = pcg(A,b1,tol,maxit,M);
```

Alternatively, you can use the following parameterized matrix-vector product function afun in place of the matrix A:

```
afun = @(x,n)gallery('moler',n)*x;
n2 = 21;
b2 = afun(ones(n2,1),n2);
[x2,flag2,rr2,iter2,rv2] = pcg(@(x)afun(x,n2),b2,tol,maxit,M);
```

Example 2


A = delsq(numgrid('C',25)); b = ones(length(A),1); [x,flag] = pcg(A,b)


flag is 1 because pcg does not converge to the default tolerance of 1e-6 within the default 20 iterations.

```
R = cholinc(A,1e-3);
[x2,flag2,relres2,iter2,resvec2] = pcg(A,b,1e-8,10,R',R)
```

flag2 is 0 because pcg converges to the tolerance of 1.2e-9 (the value of relres2) at the sixth iteration (the value of iter2) when preconditioned by the incomplete Cholesky factorization with a drop tolerance of 1e-3. resvec2(1) = norm(b) and resvec2(7) = norm(b-A*x2). You can follow the progress of pcg by plotting the relative residuals at each iteration starting from the initial estimate (iterate number 0).

```
semilogy(0:iter2,resvec2/norm(b),'-o')
xlabel('iteration number')
ylabel('relative residual')
```






References [1] Barrett, R., M. Berry, T. F. Chan, et al., *Templates for the Solution of Linear Systems: Building Blocks for Iterative Methods*, SIAM, Philadelphia, 1994.

Purpose	Piecewise Cubic Hermite Interpolating Polynomial (PCHIP)
Syntax	<pre>yi = pchip(x,y,xi) pp = pchip(x,y)</pre>
Description	yi = pchip(x,y,xi) returns vector yi containing elements corresponding to the elements of xi and determined by piecewise cubic interpolation within vectors x and y. The vector x specifies the points at which the data y is given. If y is a matrix, then the interpolation is performed for each column of y and yi is length(xi)-by-size(y,2).
	pp = pchip(x,y) returns a piecewise polynomial structure for use by $ppval$. x can be a row or column vector. y is a row or column vector of the same length as x, or a matrix with $length(x)$ columns.
	pchip finds values of an underlying interpolating function $P(x)$ at intermediate points, such that:
	• On each subinterval $x_k \le x \le x_{k+1}$, $P(x)$ is the cubic Hermite interpolant to the given values and certain slopes at the two endpoints.
	• $P(x)$ interpolates y, i.e., $P(x_j) = y_j$, and the first derivative $P'(x)$ is continuous. $P''(x)$ is probably not continuous; there may be jumps at the x_j .
	• The slopes at the x_j are chosen in such a way that $P(x)$ preserves the shape of the data and respects monotonicity. This means that, on intervals where the data are monotonic, so is $P(x)$; at points where the data has a local extremum, so does $P(x)$.

Note If y is a matrix, P(x) satisfies the above for each column of y.

Remarks	spline constructs $S(x)$ in almost the same way pchip constructs $P(x)$.
	However, spline chooses the slopes at the x_j differently, namely to make even $S''(x)$ continuous. This has the following effects:
	• spline produces a smoother result, i.e. $S''(x)$ is continuous.
	• spline produces a more accurate result if the data consists of values of a smooth function.
	• pchip has no overshoots and less oscillation if the data are not smooth.
	• pchip is less expensive to set up.
	• The two are equally expensive to evaluate.
Examples	<pre>x = -3:3; y = [-1 -1 -1 0 1 1 1]; t = -3:.01:3; p = pchip(x,y,t); s = spline(x,y,t); plot(x,y,'o',t,p,'-',t,s,'') legend('data','pchip','spline',4)</pre>



See Also

interp1, spline, ppval

References

[1] Fritsch, F. N. and R. E. Carlson, "Monotone Piecewise Cubic Interpolation," *SIAM J. Numerical Analysis*, Vol. 17, 1980, pp.238-246.

[2] Kahaner, David, Cleve Moler, Stephen Nash, *Numerical Methods and Software*, Prentice Hall, 1988.

<u>p</u>code

Purpose	Create protected function file
Syntax	pcode fun pcode *.m pcode fun1 fun2 pcodeinplace
Description	pcode fun obfuscates (i.e., <i>shrouds</i>) the code in fun.m for the purpose of protecting its proprietary source code. The encrypted code is written to pcode file fun.p in the current folder. The original .m file can be anywhere on the search path.
	If the input file resides within a package and/or class folder, then the same package and class folders are applied to the output file. See example 2, below.
	$\verb pcode *.m$ creates pcode files for all files in the current folder that have a .m file extension.
	pcode fun1 fun2 creates pcode files for the listed functions.
	pcode -inplace creates pcode files in the same folder as the script or function files. An error occurs if the files cannot be created.
	See "Protecting Your Source Code" in the MATLAB Programming Fundamentals documentation for more information.
Examples	Example 1 – PCoding Multiple Files
	Convert selected files from the sparfun folder into pcode files:
	dir([matlabroot '\toolbox\matlab\sparfun\spr*.m'])
	sprand.m sprandn.m sprandsym.m sprank.m
	cd C:\work\pcodetest pcode([matlabroot '\toolbox\matlab\sparfun\spr*.m'])
	dir

.. sprand.p sprandn.p sprandsym.p sprank.p

Example 2 – Parsing Files That Belong to a Package and/or Class

This example takes an input file that is part of a package and class, and generates a pcode file for it in a separate folder. File test.m resides in the following package and class folder:

C:\work\+mypkg\@char\test.m

Set your current working folder to empty folder math\pcodetest. This is where you will generate the pcode file. This folder has no package or class structure associated with it at this time:

```
cd C:\math\pcodetest
dir
```

. .

Generate pcode for test.m. Because the input file is part of a package and class, MATLAB creates folders +mypkg and @char so that the output file belongs to the same:

Example 3 – PCoding In Place

When you generate a pcode file inplace, MATLAB writes the output file to the same folder as the input file:

```
pcode C:\work\+mypkg\@char\test.m -inplace
dir C:\work\+mypkg\@char
```

.. test.m test.p

See Also

depfun, depdir,

pcolor

Purpose


Pseudocolor (checkerboard) plot



GUI Alternatives	To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.
Syntax	<pre>pcolor(C) pcolor(X,Y,C) pcolor(axes_handles,) h = pcolor()</pre>
Description	A pseudocolor plot is a rectangular array of cells with colors determined by C. MATLAB creates a pseudocolor plot using each set of four adjacent points in C to define a surface rectangle (i.e., cell).
	The default shading is faceted, which colors each cell with a single color. The last row and column of C are not used in this case. With shading interp, each cell is colored by bilinear interpolation of the colors at its four vertices, using all elements of C.
	The minimum and maximum elements of C are assigned the first and last colors in the colormap. Colors for the remaining elements in C are determined by a linear mapping from value to colormap element.
	pcolor(C) draws a pseudocolor plot. The elements of C are linearly mapped to an index into the current colormap. The mapping from C to the current colormap is defined by colormap and caxis.
	<pre>pcolor(X,Y,C) draws a pseudocolor plot of the elements of C at the locations specified by X and Y. The plot is a logically rectangular, two-dimensional grid with vertices at the points [X(i,j), Y(i,j)]. X and Y are vectors or matrices that specify the spacing of the grid lines. If</pre>

	<pre>X and Y are vectors, X corresponds to the columns of C and Y corresponds to the rows. If X and Y are matrices, they must be the same size as C. pcolor(axes_handles,) plots into the axes with handle axes_handle instead of the current axes (gca). h = pcolor() returns a handle to a surface graphics object.</pre>
Remarks	A pseudocolor plot is a flat surface plot viewed from above. pcolor(X,Y,C) is the same as viewing surf(X,Y,zeros(size(X)),C) using view([0 90]).
	When you use shading faceted or shading flat, the constant color of each cell is the color associated with the corner having the smallest x - y coordinates. Therefore, C(i,j) determines the color of the cell in the <i>i</i> th row and <i>j</i> th column. The last row and column of C are not used.
	When you use shading interp, each cell's color results from a bilinear interpolation of the colors at its four vertices, and all elements of C are used.
Examples	A Hadamard matrix has elements that are +1 and -1. A colormap with only two entries is appropriate when displaying a pseudocolor plot of this matrix.
	pcolor(hadamard(20)) colormap(gray(2)) axis ij axis square


pcolor



A simple color wheel illustrates a polar coordinate system.

```
n = 6;
r = (0:n)'/n;
theta = pi*(-n:n)/n;
X = r*cos(theta);
Y = r*sin(theta);
C = r*cos(2*theta);
pcolor(X,Y,C)
axis equal tight
```

pcolor



Algorithm

The number of vertex colors for pcolor(C) is the same as the number of cells for image(C). pcolor differs from image in that pcolor(C) specifies the colors of vertices, which are scaled to fit the colormap; changing the axes clim property changes this color mapping. image(C) specifies the colors of cells and directly indexes into the colormap without scaling. Additionally, pcolor(X,Y,C) can produce parametric grids, which is not possible with image.

See Also caxis, image, mesh, shading, surf, view

pdepe

Purpose	Solve initial-boundary value problems for parabolic-elliptic PDEs in 1-D
Syntax	<pre>sol = pdepe(m,pdefun,icfun,bcfun,xmesh,tspan) sol = pdepe(m,pdefun,icfun,bcfun,xmesh,tspan,options) [sol,tsol,sole,te,ie] = pdepe(m,pdefun,icfun,bcfun,xmesh, tspan,options)</pre>

Arguments

m	A parameter corresponding to the symmetry of the problem. m can be slab = 0, cylindrical = 1, or spherical = 2.
pdefun	A handle to a function that defines the components of the PDE.
icfun	A handle to a function that defines the initial conditions.
bcfun	A handle to a function that defines the boundary conditions.
xmesh	A vector $[x0, x1,, xn]$ specifying the points at which a numerical solution is requested for every value in tspan. The elements of xmesh must satisfy x0 < x1 < < xn. The length of xmesh must be >= 3.
tspan	A vector [t0, t1,, tf] specifying the points at which a solution is requested for every value in xmesh. The elements of tspan must satisfy t0 < t1 < < tf. The length of tspan must be >= 3.
options	Some options of the underlying ODE solver are available in pdepe: RelTol, AbsTol, NormControl, InitialStep, MaxStep, and Events. In most cases, default values for these options provide satisfactory solutions. See odeset for details.

Description

sol = pdepe(m,pdefun,icfun,bcfun,xmesh,tspan) solves initial-boundary value problems for systems of parabolic and elliptic PDEs in the one space variable x and time t. pdefun, icfun, and bcfun are function handles. See "Function Handles" in the MATLAB Programming documentation for more information. The ordinary differential equations (ODEs) resulting from discretization in space are integrated to obtain approximate solutions at times specified in tspan. The pdepe function returns values of the solution on a mesh provided in xmesh.

"Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide additional parameters to the functions pdefun, icfun, or bcfun, if necessary.

pdepe solves PDEs of the form:

$$c\left(x,t,u,\frac{\partial u}{\partial x}\right)\frac{\partial u}{\partial t} = x^{-m} \frac{\partial}{\partial x}\left(x^{m} f\left(x,t,u,\frac{\partial u}{\partial x}\right)\right) + s\left(x_{(2,2)}^{t},\frac{\partial u}{\partial x}\right)$$

The PDEs hold for $t_0 \le t \le t_f$ and $a \le x \le b$. The interval [a, b] must be finite. *m* can be 0, 1, or 2, corresponding to slab, cylindrical, or spherical symmetry, respectively. If m > 0, then *a* must be >= 0.

In Equation 2-2, $f(x, t, u, \partial u/\partial x)$ is a flux term and $s(x, t, u, \partial u/\partial x)$ is a source term. The coupling of the partial derivatives with respect to time is restricted to multiplication by a diagonal matrix $c(x, t, u, \partial u/\partial x)$. The diagonal elements of this matrix are either identically zero or positive. An element that is identically zero corresponds to an elliptic equation and otherwise to a parabolic equation. There must be at least one parabolic equation. An element of c that corresponds to a parabolic equation can vanish at isolated values of x if those values of x are mesh points. Discontinuities in c and/or s due to material interfaces are permitted provided that a mesh point is placed at each interface.

For $t = t_0$ and all x, the solution components satisfy initial conditions of the form

$$u(x, t_0) = u_0(x) \tag{2-3}$$

For all t and either x = a or x = b, the solution components satisfy a boundary condition of the form

$$p(x,t,u) + q(x,t) f\left(x,t,u,\frac{\partial u}{\partial x}\right) = 0$$
(2-4)

Elements of q are either identically zero or never zero. Note that the boundary conditions are expressed in terms of the flux f rather than $\partial u/\partial x$. Also, of the two coefficients, only P can depend on u.

In the call sol = pdepe(m,pdefun,icfun,bcfun,xmesh,tspan):

- m corresponds to *m*.
- xmesh(1) and xmesh(end) correspond to a and b.
- tspan(1) and tspan(end) correspond to t_0 and t_f .
- pdefun computes the terms c, f, and s (Equation 2-2). It has the form

[c,f,s] = pdefun(x,t,u,dudx)

The input arguments are scalars x and t and vectors u and dudx that approximate the solution u and its partial derivative with respect to x, respectively. c, f, and s are column vectors. c stores the diagonal elements of the matrix c (Equation 2-2).

• icfun evaluates the initial conditions. It has the form

u = icfun(x)

When called with an argument x, icfun evaluates and returns the initial values of the solution components at x in the column vector u.

• bcfun evaluates the terms P and q of the boundary conditions (Equation 2-4). It has the form

[pl,ql,pr,qr] = bcfun(xl,ul,xr,ur,t)

ul is the approximate solution at the left boundary x1 = a and ur is the approximate solution at the right boundary xr = b. pl and ql are column vectors corresponding to P and q evaluated at x1, similarly pr and qr correspond to xr. When m > 0 and a = 0, boundedness of the solution near x = 0 requires that the flux f vanish at a = 0. pdepe imposes this boundary condition automatically and it ignores values returned in pl and ql.

pdepe returns the solution as a multidimensional array sol. $u_i = ui = sol(:,:,i)$ is an approximation to the ith component of the solution vector u. The element ui(j,k) = sol(j,k,i) approximates u_i at (t, x) = (tspan(j), xmesh(k)).

ui = sol(j,:,i) approximates component i of the solution at time tspan(j) and mesh points xmesh(:). Use pdeval to compute the approximation and its partial derivative $\partial u_i/\partial x$ at points not included in xmesh. See pdeval for details.

sol = pdepe(m,pdefun,icfun,bcfun,xmesh,tspan,options) solves as above with default integration parameters replaced by values in options, an argument created with the odeset function. Only some of the options of the underlying ODE solver are available in pdepe: RelTol, AbsTol, NormControl, InitialStep, and MaxStep. The defaults obtained by leaving off the input argument options will generally be satisfactory. See odeset for details.

[sol,tsol,sole,te,ie] =

pdepe(m,pdefun,icfun,bcfun,xmesh,tspan,options) with the 'Events' property in options set to a function handle Events, solves as above while also finding where event functions g(t,u(x,t)) are zero. For each function you specify whether the integration is to terminate at a zero and whether the direction of the zero crossing matters. Three column vectors are returned by events: [value,isterminal,direction] = events(m,t,xmesh,umesh). xmesh contains the spatial mesh and umesh is the solution at the mesh points. Use pdeval to evaluate the solution between mesh points. For the I-th event function, value(i) is the value of the function, ISTERMINAL(I) = 1 if the integration is to terminate at a zero of this event function and 0 otherwise. direction(i) = 0 if all zeros are to be computed (the default), +1 if only zeros where the event function is increasing, and -1 if only zeros where the event function is decreasing. Output tsol is a column vector of times specified in tspan, prior to first terminal event. SOL(j,:,:) is the solution at T(j). TE is a vector of times at which events occur. SOLE(j,:,:) is the solution at TE(j) and indices in vector IE specify which event occurred.

If UI = SOL(j,:,i) approximates component i of the solution at time TSPAN(j) and mesh points XMESH, pdeval evaluates the approximation and its partial derivative $\partial u_i / \partial x$ at the array of points XOUT and returns them in UOUT and DUOUTDX: [UOUT,DUOUTDX] = PDEVAL(M,XMESH,UI,XOUT)

Note The partial derivative $\partial u_i / \partial x$ is evaluated here rather than the flux. The flux is continuous, but at a material interface the partial derivative may have a jump.

Remarks

• The arrays xmesh and tspan play different roles in pdepe.

tspan – The pdepe function performs the time integration with an ODE solver that selects both the time step and formula dynamically. The elements of tspan merely specify where you want answers and the cost depends weakly on the length of tspan.

xmesh – Second order approximations to the solution are made on the mesh specified in xmesh. Generally, it is best to use closely spaced mesh points where the solution changes rapidly. pdepe does *not* select the mesh in x automatically. You must provide an appropriate fixed mesh in xmesh. The cost depends strongly on the length of xmesh. When m > 0, it is not necessary to use a fine mesh near x = 0 to account for the coordinate singularity.

• The time integration is done with ode15s. pdepe exploits the capabilities of ode15s for solving the differential-algebraic equations

that arise when Equation 2-2 contains elliptic equations, and for handling Jacobians with a specified sparsity pattern.

• After discretization, elliptic equations give rise to algebraic equations. If the elements of the initial conditions vector that correspond to elliptic equations are not "consistent" with the discretization, pdepe tries to adjust them before beginning the time integration. For this reason, the solution returned for the initial time may have a discretization error comparable to that at any other time. If the mesh is sufficiently fine, pdepe can find consistent initial conditions close to the given ones. If pdepe displays a message that it has difficulty finding consistent initial conditions, try refining the mesh.

No adjustment is necessary for elements of the initial conditions vector that correspond to parabolic equations.

Examples Example 1. This example illustrates the straightforward formulation, computation, and plotting of the solution of a single PDE.

$$\pi^2 \frac{\partial u}{\partial t} = \frac{\partial}{\partial x} \left(\frac{\partial u}{\partial x} \right)$$

This equation holds on an interval $0 \le x \le 1$ for times $t \ge 0$.

The PDE satisfies the initial condition

$$u(x, 0) = \sin \pi x$$

and boundary conditions

$$u(0, t) \equiv 0$$


$$\pi e^{-t} + \frac{\partial u}{\partial x}(1, t) = 0$$

It is convenient to use subfunctions to place all the functions required by pdepe in a single M-file.

function pdex1


```
m = 0;
x = linspace(0, 1, 20);
t = linspace(0,2,5);
sol = pdepe(m,@pdex1pde,@pdex1ic,@pdex1bc,x,t);
% Extract the first solution component as u.
u = sol(:,:,1);
% A surface plot is often a good way to study a solution.
surf(x,t,u)
title('Numerical solution computed with 20 mesh points.')
xlabel('Distance x')
ylabel('Time t')
% A solution profile can also be illuminating.
figure
plot(x,u(end,:))
title('Solution at t = 2')
xlabel('Distance x')
ylabel('u(x,2)')
%
function [c,f,s] = pdex1pde(x,t,u,DuDx)
c = pi^2;
f = DuDx;
s = 0;
%
function u0 = pdex1ic(x)
u0 = sin(pi*x);
%
function [pl,ql,pr,qr] = pdex1bc(xl,ul,xr,ur,t)
pl = ul;
ql = 0;
pr = pi * exp(-t);
qr = 1;
```

In this example, the PDE, initial condition, and boundary conditions are coded in subfunctions pdex1pde, pdex1ic, and pdex1bc.



The surface plot shows the behavior of the solution.

The following plot shows the solution profile at the final value of t (i.e., t = 2).



Example 2. This example illustrates the solution of a system of PDEs. The problem has boundary layers at both ends of the interval. The solution changes rapidly for small t.

The PDEs are

$$\begin{aligned} \frac{\partial u_1}{\partial t} &= 0.024 \frac{\partial^2 u_1}{\partial x^2} - F(u_1 - u_2) \\ \frac{\partial u_2}{\partial t} &= 0.170 \frac{\partial^2 u_2}{\partial x^2} + F(u_1 - u_2) \\ \end{aligned}$$
where $F(y) &= \exp(5.73y) - \exp(-11.46y)$.

This equation holds on an interval $0 \le x \le 1$ for times $t \ge 0$.

The PDE satisfies the initial conditions

$$u_1(x, 0) \equiv 1$$
$$u_2(x, 0) \equiv 0$$

and boundary conditions

$$\begin{split} &\frac{\partial u_1}{\partial x}(0,t) \equiv 0 \\ &u_2(0,t) \equiv 0 \\ &u_1(1,t) \equiv 1 \\ &\frac{\partial u_2}{\partial x}(1,t) \equiv 0 \end{split}$$

In the form expected by pdepe, the equations are

$$\begin{bmatrix} 1 \\ 1 \end{bmatrix} \cdot * \frac{\partial}{\partial t} \begin{bmatrix} u_1 \\ u_2 \end{bmatrix} = \frac{\partial}{\partial x} \begin{bmatrix} 0.024(\partial u_1 / \partial x) \\ 0.170(\partial u_2 / \partial x) \end{bmatrix} + \begin{bmatrix} -F(u_1 - u_2) \\ F(u_1 - u_2) \end{bmatrix}$$

The boundary conditions on the partial derivatives of \boldsymbol{u} have to be written in terms of the flux. In the form expected by pdepe, the left boundary condition is

$$\begin{bmatrix} 0 \\ u_2 \end{bmatrix} + \begin{bmatrix} 1 \\ 0 \end{bmatrix} \cdot * \begin{bmatrix} 0.024(\partial u_1/\partial x) \\ 0.170(\partial u_2/\partial x) \end{bmatrix} = \begin{bmatrix} 0 \\ 0 \end{bmatrix}$$

and the right boundary condition is


```
\begin{bmatrix} u_1 - 1 \\ 0 \end{bmatrix} + \begin{bmatrix} 0 \\ 1 \end{bmatrix} \cdot * \begin{bmatrix} 0.024(\partial u_1 / \partial x) \\ 0.170(\partial u_2 / \partial x) \end{bmatrix} = \begin{bmatrix} 0 \\ 0 \end{bmatrix}
```

The solution changes rapidly for small t. The program selects the step size in time to resolve this sharp change, but to see this behavior in the plots, the example must select the output times accordingly. There are boundary layers in the solution at both ends of [0,1], so the example places mesh points near 0 and 1 to resolve these sharp changes. Often some experimentation is needed to select a mesh that reveals the behavior of the solution.


```
function pdex4
m = 0;
x = [0 \ 0.005 \ 0.01 \ 0.05 \ 0.1 \ 0.2 \ 0.5 \ 0.7 \ 0.9 \ 0.95 \ 0.99 \ 0.995 \ 1];
t = [0 \ 0.005 \ 0.01 \ 0.05 \ 0.1 \ 0.5 \ 1 \ 1.5 \ 2];
sol = pdepe(m,@pdex4pde,@pdex4ic,@pdex4bc,x,t);
u1 = sol(:,:,1);
u2 = sol(:,:,2);
fiaure
surf(x,t,u1)
title('u1(x,t)')
xlabel('Distance x')
ylabel('Time t')
figure
surf(x,t,u2)
title('u2(x,t)')
xlabel('Distance x')
ylabel('Time t')
%
                                        . . . . . . . . . .
function [c,f,s] = pdex4pde(x,t,u,DuDx)
c = [1; 1];
f = [0.024; 0.17] .* DuDx;
y = u(1) - u(2);
```

In this example, the PDEs, initial conditions, and boundary conditions are coded in subfunctions pdex4pde, pdex4ic, and pdex4bc.

The surface plots show the behavior of the solution components.



pdepe



See Also function_handle (@), pdeval, ode15s, odeset, odeget

References [1] Skeel, R. D. and M. Berzins, "A Method for the Spatial Discretization of Parabolic Equations in One Space Variable," *SIAM Journal on Scientific and Statistical Computing*, Vol. 11, 1990, pp.1–32.

Purpose	Evaluate numerical solution of PDE using output of pdepe

Syntax [uout,duoutdx] = pdeval(m,x,ui,xout)

Arguments

m	Symmetry of the problem: slab = 0, cylindrical = 1, spherical = 2. This is the first input argument used in the call to pdepe.			
xmesh	A vector $[x0, x1,, xn]$ specifying the points at which the elements of ui were computed. This is the same vector with which pdepe was called.			
ui	A vector $sol(j,:,i)$ that approximates component i of the solution at time t_f and mesh points xmesh, where sol is the solution returned by pdepe.			
xout	A vector of points from the interval [x0,xn] at which the interpolated solution is requested.			

Description [uout,duoutdx] = pdeval(m,x,ui,xout) approximates the solution u_1 and its partial derivative u_1 at points from the interval [x0,xn]. The pdeval function returns the computed values in uout and duoutdx, respectively.

Note pdeval evaluates the partial derivative $\partial u_i / \partial x$ rather than the flux f. Although the flux is continuous, the partial derivative may have a jump at a material interface.

See Also

pdepe

<u>p</u>eaks

Purpose	Example function of two variables					
	Peaks					
	$5 \\ 0 \\ 0 \\ y \\ -2 \\ -2 \\ x \\ 0 \\ y \\ -2 \\ -2 \\ x \\ 0 \\ 2 \\ -2 \\ x \\ 0 \\ 2 \\ -2 \\ x \\ 0 \\ 2 \\ x \\ 0 \\ x \\ 0 \\ 0 \\ x \\ 0 $					
Syntax	Z = peaks; Z = peaks(n); Z = peaks(V); Z = peaks(X,Y);					
	<pre>peaks; peaks(N); peaks(V); peaks(X,Y); [X,Y,Z] = peaks; [X,Y,Z] = peaks(n);</pre>					
	[X,Y,Z] = peaks(V);					
Description	peaks is a function of two variables, obtained by translating and scaling Gaussian distributions, which is useful for demonstrating mesh, surf, pcolor, contour, and so on.					
	Z = peaks; returns a 49-by-49 matrix.					
	Z = peaks(n); returns an n-by-n matrix.					
	Z = peaks(V); returns an n-by-n matrix, where n = length(V).					
	Z = peaks(X,Y); evaluates peaks at the given X and Y (which must be the same size) and returns a matrix the same size.					

peaks(...) (with no output argument) plots the peaks function with surf.

[X,Y,Z] = peaks(...); returns two additional matrices, X and Y, for parametric plots, for example, surf(X,Y,Z,del2(Z)). If not given as input, the underlying matrices X and Y are

[X,Y] = meshgrid(V,V)

where V is a given vector, or V is a vector of length n with elements equally spaced from -3 to 3. If no input argument is given, the default n is 49.

See Also meshgrid, surf

Purpose	Call Perl script using appropriate operating system executable					
Syntax	<pre>perl('perlfile') perl('perlfile',arg1,arg2,) result = perl() [result, status] = perl()</pre>					
Description	perl('perlfile') calls the Perl script perlfile, using the appropriate operating system Perl executable. Perl is included with the MATLAB software on Microsoft Windows systems, and thus MATLAB users can run M-files containing the perl function. On UNIX ¹⁵ systems, MATLAB calls the Perl interpreter available with the operating system.					
perl('perlfile',arg1,arg2,) calls the Perl script per- using the appropriate operating system Perl executable, and p arguments arg1, arg2, and so on, to perlfile.						
	result = $perl()$ returns the results of attempted Perl call to result.					
	[result, status] = perl() returns the results of attempted Perl call to result and its exit status to status.					
	It is sometimes beneficial to use Perl scripts instead of MATLAB code. The perl function allows you to run those scripts from MATLAB. Specific examples where you might choose to use a Perl script include:					
	• Perl script already exists					
	• Perl script preprocesses data quickly, formatting it in a way more easily read by MATLAB					
	• Perl has features not supported by MATLAB					
Examples	Given the Perl script, hello.pl:					
	<pre>\$input = \$ARGV[0];</pre>					
	UNIX is a registered trademark of The Open Group in the United States and other countries.					

print "Hello \$input."; At the MATLAB command line, type: perl('hello.pl','World') MATLAB displays: ans = Hello World. See Also ! (exclamation point), dos, regexp, system, unix

perms

Purpose	All possible permutations				
Syntax	P = perms(v)				
Description	P = perms(v), where v is a row vector of length n, creates a matrix whose rows consist of all possible permutations of the n elements of v. Matrix P contains n! rows and n columns.				
Examples	The command $perms([2 \ 4 \ 6])$ returns <i>all</i> the permutations of the numbers 2, 4, and 6:				
	6 4	Ļ	2		
	6 2	2	4		
	4 6	6	2		
	4 2	2	6		
	2 4	ŀ	6		
	2 6	6	4		
Limitations	This function is only practical for situations where ${\sf n}$ is less than about 15.				
See Also	nchoosek, permute, randperm				

Purpose	Rearrange dimensions of N-D array					
Syntax	<pre>B = permute(A,order)</pre>					
Description	B = permute(A, order) rearranges the dimensions of A so that they are in the order specified by the vector order. B has the same values of A but the order of the subscripts needed to access any particular element is rearranged as specified by order. All the elements of order must be unique.					
Remarks	permute and ipermute are a generalization of transpose (.') for multidimensional arrays.					
Examples	Given any matrix A, the statement permute(A,[2 1])					
	is the same as A. '.					
	For example:					
	A = [1 2; 3 4]; permute(A,[2 1]) ans = 1 3 2 4					
	The following code permutes a three-dimensional array:					
	X = rand(12,13,14); Y = permute(X,[2 3 1]); size(Y) ans = 13 14 12					
See Also	ipermute, circshift, shiftdim, reshape					

persistent

Purpose	Define persistent variable					
Syntax	persistent X Y Z					
Description	persistent X Y Z defines X, Y, and Z as variables that are local to the function in which they are declared; yet their values are retained in memory between calls to the function. Persistent variables are similar to global variables because the MATLAB software creates permanent storage for both. They differ from global variables in that persistent variables are known only to the function in which they are declared. This prevents persistent variables from being changed by other functions or from the MATLAB command line.					
	Whenever you clear or modify a function that is in memory, MATLAB also clears all persistent variables declared by that function. To keep a function in memory until MATLAB quits, use mlock.					
	If the persistent variable does not exist the first time you issue the persistent statement, it is initialized to the empty matrix.					
	It is an error to declare a variable persistent if a variable with the same name exists in the current workspace. MATLAB also errors if you declare any of a function's input or output arguments as persistent within that same function. For example, the following persistent declaration is invalid:					
	function myfun(argA, argB, argC) persistent argB					
Remarks	There is no function form of the persistent command (i.e., you cannot use parentheses and quote the variable names).					
Example	This function writes a large array to a spreadsheet file and then reads several rows from the same file. Because you only need to write the array to the spreadsheet one time, the program tests whether an array can be read from the file and, if so, does not waste time in repeating that task. By defining the dblarray variable as persistent, you can easily check whether the array has been read from the spreadsheet file.					

Here is the arrayToXLS function:

```
function arrayToXLS(A, xlsfile, x1, x2)
persistent dblArray;
if isempty(dblArray)
    disp 'Writing spreadsheet file ...'
    xlswrite(xlsfile, A);
end
disp 'Reading array from spreadsheet ...'
dblArray = xlsread(xlsfile, 'Sheet1', [x1 ':' x2])
fprintf('\n');
```

Run the function three times and observe the time elapsed for each run. The second and third run take approximately one tenth the time of the first run in which the function must create the spreadsheet:

```
largeArray = rand(4000, 200);
tic, arrayToXLS(largeArray, 'myTest.xls','E254', 'J256'),
                                                            toc
Writing spreadsheet file ...
Reading array from spreadsheet ...
dblArray =
    0.0982
              0.3783
                        0.1264
                                  0.7880
                                            0.1902
                                                      0.5811
    0.2251
              0.2704
                        0.5682
                                  0.7271
                                            0.8028
                                                      0.2834
    0.6453
              0.5568
                        0.8254
                                  0.4961
                                            0.9096
                                                      0.5402
Elapsed time is 8.990525 seconds.
tic, arrayToXLS(largeArray, 'myTest.xls', 'E257', 'J258'), toc
Reading array from spreadsheet ...
dblArray =
    0.4620
              0.3781
                        0.6386
                                  0.5930
                                            0.0946
                                                      0.4865
```

0.5188

0.6702

0.8709

0.1251

0.1605

0.2138

persistent

```
Elapsed time is 0.912534 seconds.
                    tic, arrayToXLS(largeArray, 'myTest.xls', 'E259', 'J262'), toc
                    Reading array from spreadsheet ...
                    dblArray =
                        0.7015
                                   0.6588
                                             0.4023
                                                       0.0359
                                                                  0.4512
                                                                            0.6097
                        0.1308
                                   0.6441
                                             0.0431
                                                       0.6396
                                                                  0.7481
                                                                            0.8688
                        0.8278
                                   0.2686
                                             0.5475
                                                       0.8550
                                                                  0.5896
                                                                            0.1080
                                                                  0.2461
                        0.9437
                                   0.1671
                                             0.0505
                                                       0.1203
                                                                            0.7306
                    Elapsed time is 0.928843 seconds.
                  Now clear the arrayToXLS function from memory and observe that
                  running it takes much longer again:
                    clear functions
                    tic, arrayToXLS(largeArray, 'myTest.xls', 'E263', 'J264'), toc
                    Writing spreadsheet file ...
                    Reading array from spreadsheet ...
                    dblArray =
                        0.6292
                                   0.7788
                                             0.0732
                                                        0.6481
                                                                  0.9299
                                                                            0.8631
                        0.7700
                                   0.5181
                                             0.9805
                                                       0.5092
                                                                  0.8658
                                                                            0.4070
                    Elapsed time is 7.603461 seconds.
See Also
                  global, clear, mislocked, mlock, munlock, isempty
```

Purpose	Ratio of circle's circumference to its diameter				
Syntax	pi				
Description	pi returns the floating-point number nearest the value of π . The expressions 4*atan(1) and imag(log(-1)) provide the same value.				
Examples	Imples Find the sine of π :				
	sin(pi)				
	returns				
	ans =				
	1.2246e-16				


The expression sin(pi) is not exactly zero because pi is not exactly π .

Purpose Pie chart



GUI Alternatives	To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.						
Syntax	<pre>pie(X) pie(X,explode) pie(,labels) pie(axes_handle,) h = pie()</pre>						
Description	<pre>pie(X) draws a pie chart using the data in X. Each element in X is represented as a slice in the pie chart. pie(X,explode) offsets a slice from the pie. explode is a vector or matrix of zeros and nonzeros that correspond to X. A nonzero value offsets the corresponding slice from the center of the pie chart, so that X(i,j) is offset from the center if explode(i,j) is nonzero. explode must be the same size as X. pie(,labels) specifies text labels for the slices. The number of labels must equal the number of elements in X. For example, pie(1:3,{'Taxes', 'Expenses', 'Profit'}) pie(axes_handle,) plots into the axes with the handle axes_handle instead of into the current axes (gca). h = pie() returns a vector of handles to patch and text graphics objects.</pre>						

- **Remarks** The values in X are normalized via X/sum(X) to determine the area of each slice of the pie. If sum(X) 1, the values in X directly specify the area of the pie slices. MATLAB draws only a partial pie if sum(X) < 1.
- **Examples** Emphasize the second slice in the chart by setting its corresponding explode element to 1.






Purpose 3-D pie chart



GUI Alternatives	To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulat graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.						
Syntax	<pre>pie3(X) pie3(X,explode) pie3(,labels) pie3(axes_handle,) h = pie3()</pre>						
Description	<pre>pie3(X) draws a three-dimensional pie chart using the data in X. Each element in X is represented as a slice in the pie chart. pie3(X,explode) specifies whether to offset a slice from the center of the pie chart. X(i,j) is offset from the center of the pie chart if explode(i,j) is nonzero. explode must be the same size as X. pie3(,labels) specifies text labels for the slices. The number of labels must equal the number of elements in X. For example, pie3(1:3,{'Taxes', 'Expenses', 'Profit'}) pie3(axes_handle,) plots into the axes with the handle</pre>						
	axes_handle instead of into the current axes (gca).						
	h = pie3() returns a vector of handles to patch, surface, and text graphics objects.						

- **Remarks** The values in X are normalized via X/sum(X) to determine the area of each slice of the pie. If sum(X) 1, the values in X directly specify the area of the pie slices. MATLAB draws only a partial pie if sum(X) < 1.
- **Examples** Offset a slice in the pie chart by setting the corresponding explode element to 1:





pie

pinv

Purpose	Moore-Penrose pseudoinverse of matrix				
Syntax	B = pinv(A) B = pinv(A,tol)				
Definition	The Moore-Penrose pseudoinverse is a matrix B of the same dimensions as A' satisfying four conditions:				
	A*B*A = A B*A*B = B A*B is Hermitian B*A is Hermitian				
	The computation is based on $svd(A)$ and any singular values less than tol are treated as zero.				
Description	B = pinv(A) returns the Moore-Penrose pseudoinverse of A.				
	<pre>B = pinv(A,tol) returns the Moore-Penrose pseudoinverse and overrides the default tolerance, max(size(A))*norm(A)*eps.</pre>				
Examples	If A is square and not singular, then $pinv(A)$ is an expensive way to compute $inv(A)$. If A is not square, or is square and singular, then $inv(A)$ does not exist. In these cases, $pinv(A)$ has some of, but not all, the properties of $inv(A)$.				
	If A has more rows than columns and is not of full rank, then the overdetermined least squares problem				
	<pre>minimize norm(A*x-b)</pre>				
	does not have a unique solution. Two of the infinitely many solutions are				
	x = pinv(A)*b				
	and				
	y = A b				

These two are distinguished by the facts that norm(x) is smaller than the norm of any other solution and that y has the fewest possible nonzero components.

For example, the matrix generated by

A = magic(8); A = A(:, 1:6)

is an 8-by-6 matrix that happens to have rank(A) = 3.

А	=					
	64	2	3	61	60	6
	9	55	54	12	13	51
	17	47	46	20	21	43
	40	26	27	37	36	30
	32	34	35	29	28	38
	41	23	22	44	45	19
	49	15	14	52	53	11
	8	58	59	5	4	62

The right-hand side is $b = 260 \times (8, 1)$,

```
b =
260
260
260
260
260
260
260
260
260
```

The scale factor 260 is the 8-by-8 magic sum. With all eight columns, one solution to $A^*x = b$ would be a vector of all 1's. With only six columns, the equations are still consistent, so a solution exists, but it is not all 1's. Since the matrix is rank deficient, there are infinitely many solutions. Two of them are

$$x = pinv(A)*b$$

which is

x = 1.1538 1.4615 1.3846 1.3846 1.4615 1.1538

and

```
y = A \setminus b
```

which produces this result.

```
Warning: Rank deficient, rank = 3 tol = 1.8829e-013.
y =
4.0000
5.0000
0
0
-1.0000
```

Both of these are exact solutions in the sense that $norm(A^*x-b)$ and $norm(A^*y-b)$ are on the order of roundoff error. The solution x is special because

norm(x) = 3.2817

is smaller than the norm of any other solution, including

norm(y) = 6.4807

On the other hand, the solution y is special because it has only three nonzero components.

See Also inv, qr, rank, svd

planerot

Purpose	Givens plane rotation
Syntax	[G,y] = planerot(x)
Description	[G,y] = planerot(x) where x is a 2-component column vector, returns a 2-by-2 orthogonal matrix G so that $y = G*x$ has $y(2) = 0$.
Examples	<pre>x = [3 4]; [G,y] = planerot(x') G =</pre>
	y = 5 0
See Also	qrdelete, qrinsert

audioplayer.play

Purpose	Play audio from audioplayer object
Syntax	play(playerObj) play(playerObj, start) play(playerObj, [start stop])
Description	play(<i>playerObj</i>) plays the audio associated with audioplayer object <i>playerObj</i> from beginning to end.
	<pre>play(playerObj, start) plays audio from the sample indicated by start to the end.</pre>
	play(<i>playerObj</i> , [<i>start stop</i>]) plays audio from the sample indicated by <i>start</i> to the sample indicated by <i>stop</i> .
Example	<pre>Load the demo file handel.mat and play the first 3 seconds of audio: load handel.mat; handel = audioplayer(y, Fs); play(handel, [1 handel.SampleRate*3]);</pre>
See Also	audioplayer playblocking
How To	• "Playing Audio"

Purpose	Play audio from audiorecorder object
Syntax	<pre>player = play(recObj) player = play(recObj, start) player = play(recObj, [start stop])</pre>
Description	<pre>player = play(recObj) plays the audio associated with audiorecorder object recObj from beginning to end, and returns an audioplayer object.</pre>
	<pre>player = play(recObj, start) plays audio from the sample indicated by start to the end.</pre>
	<pre>player = play(recObj, [start stop]) plays audio from the sample indicated by start to the sample indicated by stop.</pre>
Examples	Record 5 seconds of your speech with a microphone, and play it back. Display the properties of the audioplayer object.
	myVoice = audiorecorder;
	disp('Start speaking.'); recordblocking(myVoice, 5); disp('End of recording. Playing back');
	<pre>playerObj = play(myVoice);</pre>
	disp('Properties of playerObj:'); get(playerObj)
	Play back only the first 3 seconds of the speech recorded in the previous example:
_	<pre>play(myVoice, [1 myVoice.SampleRate*3]);</pre>

See Also audioplayer | audiorecorder

Purpose	Play audio from audioplayer object, holding control until playback completes
Syntax	playblocking(<i>playerObj</i>) playblocking(<i>playerObj</i> , start) playblocking(<i>playerObj</i> , [start stop])
Description	playblocking(<i>playerObj</i>) plays the audio associated with audioplayer object <i>playerObj</i> from beginning to end. playblocking does not return control until playback completes.
	playblocking(<i>playerObj</i> , <i>start</i>) plays audio from the sample indicated by <i>start</i> to the end.
	playblocking(<i>playerObj</i> , [<i>start stop</i>]) plays audio from the sample indicated by <i>start</i> to the sample indicated by <i>stop</i> .
Examples	Load the demo files chirp.mat and gong.mat. Play with and without blocking.
	chirpData = load('chirp.mat'); chirpObj = audioplayer(chirpData.y, chirpData.Fs);
	gongData = load('gong.mat'); gongObj = audioplayer(gongData.y, gongData.Fs);
	% Play with blocking, one after the other. playblocking(chirpObj); playblocking(gongObj);
	% Play without blocking: audio overlaps. play(chirpObj); play(gongObj);


Load the demo file <code>handel.mat</code> and play the first 3 seconds. Beep when finished.

```
load handel.mat;
handel = audioplayer(y, Fs);
playblocking(handel, [1 handel.SampleRate*3]);
beep;
See Also audioplayer | play
How To · "Playing Audio"
```

playshow


Purpose	Run M-file demo (deprecated; use echodemo instead)
Syntax	playshow filename
Description	playshow filename runs filename, which is a demo. Replace playshow filename with echodemo filename. Note that other arguments supported by playshow are not supported by echodemo.
See Also	demo, echodemo, helpbrowser

Purpose	2-D line plot
Syntax	<pre>plot(Y) plot(X1,Y1,,Xn,Yn) plot(X1,Y1,LineSpec,,Xn,Yn,LineSpec) plot(X1,Y1,LineSpec,'<i>PropertyName</i>',PropertyValue) plot(axes_handle,X1,Y1,LineSpec,'<i>PropertyName</i>',PropertyValue) h = plot(X1,Y1,LineSpec,'<i>PropertyName</i>',PropertyValue)</pre>
Description	<pre>plot(Y) plots the columns of Y versus the index of each value when Y is a real number. For complex Y, plot(Y) is equivalent to plot(real(Y),imag(Y)).</pre>
	plot(X1,Y1,,Xn,Yn) plots each vector Yn versus vector Xn on the same axes. If one of Yn or Xn is a matrix and the other is a vector, plots the vector versus the matrix row or column with a matching dimension to the vector. If Xn is a scalar and Yn is a vector, plots discrete Yn points vertically at Xn. If Xn or Yn are complex, imaginary components are ignored. plot automatically chooses colors and line styles in the order specified by ColorOrder and LineStyleOrder properties of current axes.
	plot(X1,Y1,LineSpec,,Xn,Yn,LineSpec) plots lines defined by the Xn,Yn,LineSpec triplets, where LineSpec specifies the line type, marker symbol, and color. You can mix Xn,Yn,LineSpec triplets with Xn,Yn pairs: plot(X1,Y1,X2,Y2,LineSpec,X3,Y3).
	plot(X1,Y1,LineSpec,' <i>PropertyName</i> ',PropertyValue) manipulates plot characteristics by setting lineseries properties (of lineseries graphics objects created by plot). Enter properties as one or more name and value pairs.
	<pre>plot(axes_handle,X1,Y1,LineSpec,'PropertyName',PropertyValue) plots using axes with the handle axes_handle instead of the current axes (gca).</pre>
	<pre>h = plot(X1,Y1,LineSpec, 'PropertyName', PropertyValue) returns a column vector of handles to lineseries objects, one handle per line.</pre>



Create line plot using specific line width, marker color, and marker size:


```
x = -pi:pi/10:pi;
y = tan(sin(x)) - sin(tan(x));
plot(x,y,'--rs','LineWidth',2,...
'MarkerEdgeColor','k',...
```



'MarkerFaceColor','g',... 'MarkerSize',10)


Modify axis tick marks and tick labels:

```
x = -pi:.1:pi;
y = sin(x);
plot(x,y)
set(gca,'XTick',-pi:pi/2:pi)
set(gca,'XTickLabel',{'-pi','-pi/2','0','pi/2','pi'})
```



Add a plot title, axis labels, and annotations:

```
x = -pi:.1:pi;
y = sin(x);
p = plot(x,y)
set(gca,'XTick',-pi:pi/2:pi)
set(gca,'XTickLabel',{'-pi','-pi/2','0','pi/2','pi'})
xlabel('-\pi \leq \Theta \leq \pi')
ylabel('sin(\Theta)')
title('Plot of sin(\Theta)')
% \Theta appears as a Greek symbol (see String)
% Annotate the point (-pi/4, sin(-pi/4))
text(-pi/4,sin(-pi/4),'\leftarrow sin(-\pi\div4)',...
'HorizontalAlignment','left')
% Change the line color to red and
% set the line width to 2 points
```



set(p,'Color','red','LineWidth',2)

Plot multiple line plots on the same axes:

```
plot(rand(12,1))
% hold axes and all lineseries properties, such as
% ColorOrder and LineStyleOrder, for the next plot
hold all
plot(randn(12,1))
```


Set line color to be always black and line style order to cycle through solid, dash-dot, dash-dash, and dotted line styles:

	<pre>set(0,'DefaultAxesColorOrder',[0 0 0], 'DefaultAxesLineStyleOrder','- :') plot(rand(12,1)) hold all plot(rand(12,1)) hold all plot(rand(12,1))</pre>
Alternatives	To plot variables in the MATLAB workspace:
	I In the MATLAB workspace browser, select one or more variables.
	2 Choose the plot type from the menu.
See Also	axis axes bar gca grid hold legend line lineseries properties LineSpec LineWidth loglog MarkerEdgeColor MarkerFaceColor MarkerSize plot3 plotyy semilogx semilogy subplot title xlabel xlim ylabel ylim
How To	Editing Plot Characteristics
	Creating Line Plots
	Annotating Graphs
	Creating Graphics from the Workspace Browser
	 "Axes Objects — Defining Coordinate Systems for Graphs"


Purpose	Plot time series
Syntax	plot(ts) plot(tsc.tsname) plot(,linespec) plot(,'Property1',value1,'Property2',value2,)
Description	<pre>plot(ts) plots the time-series data ts against time and interpolates values between samples by using either zero-order-hold ('zoh') or linear interpolation (the default). The plot displays in the current axes. A figure and axes is created if none exists.</pre>
	plot(tsc.tsname) plots the timeseries object tsname that is part of the tscollection tsc.
	plot(,linespec) plots a line graph and applies the specified linespec to lines and/or markers.
	plot(,'Property1',value1,'Property2',value2,) plots a line graph using the values specified for lineseries properties.
Remarks	The timeseries/plot method generates titles and axis labels automatically, as the following example illustrates. These labels are:
	• Plot Title — 'Time Series Plot: <name>'</name>
	• X-Axis Label — 'Time (<units>)'</units>
	• Y-Axis Label — ' <name>'</name>
	where <name> is the string assigned to ts.Name, or by default, 'unnamed'. <units> is the value of the ts.TimeInfo.Units field, which defaults to 'seconds'.</units></name>
	You can place new time-series data on a time-series plot (by setting hold on, for example, and issuing another timeseries/plot command). When you add data to a plot, the title and axis labels are replaced by blank strings to avoid labeling confusion. You can add your own labels after plotting using the title, xlabel, and ylabel commands.

Example


	Time-series events, when defined, are marked in the plot by a circular marker with red fill. You can also specify markers for all data points using a linespec or property/value syntax in addition to any event markers your data defines. The event markers plot on top of the markers you define.
	The value assigned to ts.DataInfo.Interpolation.Name controls the type of interpolation used when plotting and resampling time series data. Invoke the timeseries method setinterpmethod to change default linear interpolation to zero-order hold interpolation (staircase). This method creates a new timeseries object, with which you can overwrite the original one if you want. For example, to cause time series ts to use zero-order hold interpolation, type the following:
	<pre>ts = ts.setinterpmethod('zoh');</pre>
•	Create two time-series objects from traffic count data and plot them in sequence on the same axes. Add an event to one series, which is automatically displayed by a red marker.
	<pre>load count.dat; count1=timeseries(count(:,1),1:24); count1.Name = 'Oak St. Traffic Count'; count1.TimeInfo.Units = 'Hours'; plot(count1,':b'), grid on</pre>




% Obtain time of maximum value and add it as an event [~,index] = max(count1.Data); max_event = tsdata.event('peak',count1.Time(index)); max_event.Units = 'hours'; % Add the event to the time series count1 = addevent(count1,max_event); % Replace plot with new one showing the event plot(count1,'.-b'), grid on



```
% Make a new ts object from column 2 of the same data source
count2=timeseries(count(:,2),1:24);
count2.Name = 'Maple St. Traffic Count';
count2.TimeInfo.Units = 'Hours';
% Turn hold on to add the new data to the plot
hold on
% The plot method does not add labels to a held plot
% Use property/value pair to customize markers
plot(count2,'s-m','MarkerSize',6),
```



% Labels are erased, so generate them manually title('Time Series: Oak Street and Maple Street') xlabel('Hour of day') ylabel('Vehicle count') % Add a legend in the upper left legend('Oak St.','Maple St.','Location','northwest')




See Also setinterpmethod, timeseries, tscollection, tsdata.event, tsprops, plot

Purpose 3-D	line plot
-------------	-----------



GUI Alternatives	To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.
Syntax	<pre>plot3(X1,Y1,Z1,) plot3(X1,Y1,Z1,LineSpec,) plot3(,'PropertyName',PropertyValue,) h = plot3()</pre>
Description	The plot3 function displays a three-dimensional plot of a set of data points. plot3(X1,Y1,Z1,), where X1, Y1, Z1 are vectors or matrices, plots one or more lines in three-dimensional space through the points whose coordinates are the elements of X1, Y1, and Z1. plot3(X1,Y1,Z1,LineSpec,) creates and displays all lines defined by the Xn,Yn,Zn,LineSpec quads, where LineSpec is a line specification that determines line style, marker symbol, and color of the plotted lines.
	plot3(, ' <i>PropertyName</i> ', PropertyValue,) sets properties to the specified property values for all line graphics objects created by plot3.
	h = plot3() returns a column vector of handles to lineseries graphics objects, with one handle per object.

Remarks	If one or more of $X1$, $Y1$, $Z1$ is a vector, the vectors are plotted versus the rows or columns of the matrix, depending whether the vectors' lengths equal the number of rows or the number of columns.	
	You can mix Xn,Yn,Zn triples with Xn,Yn,Zn, <i>LineSpec</i> quads, for example,	
	plot3(X1,Y1,Z1,X2,Y2,Z2,LineSpec,X3,Y3,Z3)	
	See LineSpec and plot for information on line types and markers.	
Examples	Plot a three-dimensional helix.	
t = 0:pi/50:10*pi;		
	<pre>plot3(sin(t),cos(t),t) </pre>	
	grid on	
	axis square	



See Also axis, bar3, grid, line, LineSpec, loglog, plot, semilogx, semilogy, subplot

plotbrowser



GUI Alternatives	Click the larger Plotting Tools icon on the figure toolbar to collectively enable plotting tools, and the smaller icon to collectively disable them. Open or close the Plot Browser tool from the figure's View menu. For details, see "The Plot Browser" in the MATLAB Graphics documentation.
Syntax	plotbrowser('on') plotbrowser('off') plotbrowser('toggle') plotbrowser plotbrowser(figure_handle,)
Description	<pre>plotbrowser('on') displays the Plot Browser on the current figure. plotbrowser('off') hides the Plot Browser on the current figure. plotbrowser('toggle') or plotbrowser toggles the visibility of the Plot Browser on the current figure. plotbrowser(figure_handle,) shows or hides the Plot Browser on the figure specified by figure_handle.</pre>
See Also	plottools, figurepalette, propertyeditor

Purpose	Interactively edit and annotate plots
---------	---------------------------------------

- Syntax plotedit on
 plotedit off
 plotedit
 plotedit(h)
 plotedit('state')
 plotedit(h,'state')
- **Description** plotedit on starts plot edit mode for the current figure, allowing you to use a graphical interface to annotate and edit plots easily. In plot edit mode, you can label axes, change line styles, and add text, line, and arrow annotations.

plotedit off ends plot mode for the current figure.

plotedit toggles the plot edit mode for the current figure.

plotedit(h) toggles the plot edit mode for the figure specified by figure
handle h.

plotedit('state') specifies the plotedit state for the current figure. Values for state can be as shown.


Value for state	Description
on	Starts plot edit mode
off	Ends plot edit mode
showtoolsmenu	Displays the Tools menu in the menu bar
hidetoolsmenu	Removes the Tools menu from the menu bar

Note hidetoolsmenu is intended for GUI developers who do not want the **Tools** menu to appear in applications that use the figure window.

plotedit

plotedit(h,'state') specifies the plotedit state for figure handle h.

Remarks Plot Editing Mode Graphical Interface Components



Examples Start plot edit mode for figure 2.

plotedit(2)

End plot edit mode for figure 2.

plotedit(2, 'off')

Hide the **Tools** menu for the current figure:


plotedit('hidetoolsmenu')

See Also axes, line, open, plot, print, saveas, text, propedit

<u>plo</u>tmatrix

Purpose	Scatter plot matrix	
Syntax	<pre>plotmatrix(X,Y) plotmatrix(X)</pre>	
	plotmatrix(X) plotmatrix(,'LineSpec')	
	<pre>[H,AX,BigAx,P] = plotmatrix()</pre>	
Description	plotmatrix(X,Y) scatter plots the columns of X against the columns of Y. If X is p -by- m and Y is p -by- n , plotmatrix produces an n -by- m matrix of axes.	
	plotmatrix(X) is the same as $plotmatrix(X,X)$, except that the diagonal is replaced by $hist(X(:,i))$.	
	<pre>plotmatrix(,'LineSpec') uses a LineSpec to create the scatter plot. The default is '.'.</pre>	
	[H,AX,BigAx,P] = plotmatrix() returns a matrix of handles to the objects created in H, a matrix of handles to the individual subaxes in AX, a handle to a big (invisible) axes that frames the subaxes in BigAx, and a matrix of handles for the histogram plots in P. BigAx is left as the current axes so that a subsequent title, xlabel, or ylabel command is centered with respect to the matrix of axes.	
Examples	Generate plots of random data.	
	x = randn(50,3); y = x*[-1 2 1;2 0 1;1 -2 3;]'; plotmatrix(y,'*r')	

plotmatrix




See Also

scatter, scatter3

plottools

Purpose

Show or hide plot tools



GUI Alternatives	Click the larger Plotting Tools icon on the figure toolbar to collectively enable plotting tools, and the smaller icon to collectively disable them. Individually select the Figure Palette , Plot Browser , and Property Editor tools from the figure's View menu. For details, see "Plotting Tools — Interactive Plotting" in the MATLAB Graphics
Syntax	<pre>documentation. plottools('on') plottools('off') plottools plottools(figure_handle,)</pre>

plottools(...,'tool')

Description plottools('on') displays the Figure Palette, Plot Browser, and Property Editor on the current figure, configured as you last used them.

plottools('off') hides the Figure Palette, Plot Browser, and Property Editor on the current figure.

plottools with no arguments, is the same as plottools('on')

plottools(figure_handle,...) displays or hides the plot tools on the specified figure instead of on the current figure.

plottools(..., 'tool') operates on the specified tool only. tool can be one of the following strings:

- figurepalette
- plotbrowser
- propertyeditor

Note The first time you open the plotting tools, all three of them appear, grouped around the current figure as shown above. If you close, move, or undock any of the tools, MATLAB remembers the configuration you left them in and restores it when you invoke the tools for subsequent figures, both within and across MATLAB sessions.

See Also figurepalette, plotbrowser, propertyeditor

plotyy

Purpose 2-D line plots with y-axes on both left and right side



GUI Alternatives	To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see "Plotting Tools — Interactive Plotting" in the MATLAB Graphics documentation and "Creating Plots from the Workspace Browser" in the MATLAB Desktop Tools documentation.
Syntax	<pre>plotyy(X1,Y1,X2,Y2) plotyy(X1,Y1,X2,Y2,function) plotyy(X1,Y1,X2,Y2,'function1','function2') [AX,H1,H2] = plotyy()</pre>
Description	<pre>plotyy(X1,Y1,X2,Y2) plots X1 versus Y1 with y-axis labeling on the left and plots X2 versus Y2 with y-axis labeling on the right. plotyy(X1,Y1,X2,Y2,function) uses the specified plotting function to</pre>
	produce the graph. function can be either a function handle or a string specifying plot, semilogx, semilogy, loglog, stem, or any MATLAB function that accepts the syntax
	<pre>h = function(x,y)</pre>
	For example,
	plotyy(x1,y1,x2,y2,@loglog) % function handle plotyy(x1,y1,x2,y2,'loglog') % string
	Function handles enable you to access user-defined subfunctions and can provide other advantages. See @ for more information on using

plotyy(X1,Y1,X2,Y2,'function1','function2') uses function1(X1,Y1) to plot the data for the left axis and function2(X2,Y2) to plot the data for the right axis.

[AX,H1,H2] = plotyy(...) returns the handles of the two axes created in AX and the handles of the graphics objects from each plot in H1 and H2. AX(1) is the left axes and AX(2) is the right axes.

Examples This example graphs two mathematical functions using plot as the plotting function. The two *y*-axes enable you to display both sets of data on one graph even though relative values of the data are quite different.

x = 0:0.01:20; y1 = 200*exp(-0.05*x).*sin(x); y2 = 0.8*exp(-0.5*x).*sin(10*x); [AX,H1,H2] = plotyy(x,y1,x,y2,'plot');

You can use the handles returned by plotyy to label the axes and set the line styles used for plotting. With the axes handles you can specify the YLabel properties of the left- and right-side y-axis:

```
set(get(AX(1),'Ylabel'),'String','Slow Decay')
set(get(AX(2),'Ylabel'),'String','Fast Decay')
```


Use the xlabel and title commands to label the x-axis and add a title:


```
xlabel('Time (\musec)')
title('Multiple Decay Rates')
```

Use the line handles to set the LineStyle properties of the left- and right-side plots:

```
set(H1,'LineStyle','--')
set(H2,'LineStyle',':')
```

plotyy





See "Using Multiple X- and Y-Axes" for more information.

Purpose	Simplex containing specified location	
Syntax	SI = pointLocation(SI = pointLocation(SI = pointLocation([SI, BC] = pointLocation(DT,QX,QY) DT,QX,QY,QZ)
Description	SI = pointLocation(DT,QX) returns the indices SI of the enclosing simplex (triangle/tetrahedron) for each query point location in QX. The enclosing simplex for point $QX(k,:)$ is $SI(k)$. pointLocation returns NaN for all points outside the convex hull.	
	SI = pointLocation(DT,QX,QY) and SI = pointLocation(DT,QX,QY,QZ) allow the query point locations to be specified in alternative column vector format when working in 2-D and 3-D.	
	[SI, BC] = pointLoca coordinates BC.	ation(DT,) returns the barycentric
Input Arguments	DT QX	Delaunay triangulation. Matrix of size mpts-by-ndim, mpts being the number of query points.
Output Arguments	SI	Column vector of length mpts containing the indices of the enclosing simplex for each query point. mpts is the number of query points.
	BC	BC is a mpts-by-ndim matrix, each row BC(i,:) represents the barycentric coordinates of QX(i,:) with respect to the enclosing simplex SI(i).

DelaunayTri.pointLocation

Examples

Example 1

Create a 2-D Delaunay triangulation:

X = rand(10,2); dt = DelaunayTri(X);

Find the triangles that contain specified query points:

qrypts = [0.25 0.25; 0.5 0.5]; triids = pointLocation(dt, qrypts)

Example 2

Create a 3-D Delaunay triangulation:

x = rand(10,1); y = rand(10,1); z = rand(10,1); dt = DelaunayTri(x,y,z);

Find the triangles that contain specified query points and evaluate the barycentric coordinates:


qrypts = [0.25 0.25 0.25; 0.5 0.5 0.5]; [tetids, bcs] = pointLocation(dt, qrypts)


See Also nearestNeighbor


PurposeTransform polar or cylindrical coordinates to CartesianSyntax[X,Y] = pol2cart(THETA,RHO)
[X,Y,Z] = pol2cart(THETA,RHO,Z)Description[X,Y] = pol2cart(THETA,RHO) transforms the polar coordinate data
stored in corresponding elements of THETA and RHO to two-dimensional
Cartesian, or xy, coordinates. The arrays THETA and RHO must be the
same size (or either can be scalar). The values in THETA must be in
radians.

xyz, [X,Y,Z] = pol2cart(THETA,RHO,Z) transforms the cylindrical coordinate data stored in corresponding elements of THETA, RHO, and Z to three-dimensional Cartesian, or coordinates. The arrays THETA, RHO, and Z must be the same size (or any can be scalar). The values in THETA must be in radians.

Algorithm The mapping from polar and cylindrical coordinates to Cartesian coordinates is:







Cylindrical to Cartesian Mapping

theta = atan2(y,x)rho = $sqrt(x.^2 + y.^2)$ z = z


pol2cart


See Also cart2pol, cart2sph, sph2cart

Purpose	Polar coordinate plot
GUI Alternatives	To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.
Syntax	polar(theta,rho) polar(theta,rho,LineSpec) polar(axes_handle,) h = polar()
Description	The polar function accepts polar coordinates, plots them in a Cartesian plane, and draws the polar grid on the plane.
	polar(theta,rho) creates a polar coordinate plot of the angle theta versus the radius rho. theta is the angle from the x-axis to the radius vector specified in radians; rho is the length of the radius vector specified in dataspace units.
	polar(theta,rho,LineSpec) LineSpec specifies the line type, plot symbol, and color for the lines drawn in the polar plot.
	<pre>polar(axes_handle,) plots into the axes with the handle axes_handle instead of into the current axes (gca).</pre>
	h = polar() returns the handle of a line object in h .
Remarks	Negative r values reflect through the origin, rotating by pi (since (theta,r) transforms to (r*cos(theta), r*sin(theta))). If you want different behavior, you can manipulate r prior to plotting. For example, you can make r equal to max(0,r) or abs(r).

polar

Examples Create a simple polar plot using a dashed red line:





Purpose	Polynomial with specified roots			
Syntax	<pre>p = poly(A) p = poly(r)</pre>			
Description	p = poly(A) where A is an n-by-n matrix returns an n+1 element row vector whose elements are the coefficients of the characteristic polynomial, $det(sl - A)$. The coefficients are ordered in descending powers: if a vector c has n+1 components, the polynomial it represents is $c_1s^n + \ldots + c_ns + c_{n+1}$			
	p = poly(r) where r is a vector returns a row vector whose elements are the coefficients of the polynomial whose roots are the elements of r.			
Remarks	Note the relationship of this command to r = roots(p) which returns a column vector whose elements are the roots of the polynomial specified by the coefficients row vector p. For vectors, roots and poly are inverse functions of each other, up to ordering, scaling, and roundoff error.			
Examples	MATLAB displays polynomials as row vectors containing the coefficients ordered by descending powers. The characteristic equation of the matrix $A = \begin{bmatrix} 1 & 2 & 3 \\ 4 & 5 & 6 \\ 7 & 8 & 0 \end{bmatrix}$ is returned in a row vector by poly: p = poly(A) $p =$			

```
1 -6 -72 -27
```

The roots of this polynomial (eigenvalues of matrix A) are returned in a column vector by roots:

```
r = roots(p)
r =
    12.1229
    -5.7345
    -0.3884
```

Algorithm

The algorithms employed for poly and roots illustrate an interesting aspect of the modern approach to eigenvalue computation. poly(A) generates the characteristic polynomial of A, and roots(poly(A)) finds the roots of that polynomial, which are the eigenvalues of A. But both poly and roots use eig, which is based on similarity transformations. The classical approach, which characterizes eigenvalues as roots of the characteristic polynomial, is actually reversed.

If A is an n-by-n matrix, poly(A) produces the coefficients c(1) through c(n+1), with c(1) = 1, in

$$det(\lambda I - A) = c_1 \lambda^n + \dots + c_n \lambda + c_{n+1}$$

The algorithm is

This recursion is easily derived by expanding the product.


$$(\lambda - \lambda_1)(\lambda - \lambda_2)...(\lambda - \lambda_n)$$

It is possible to prove that poly(A) produces the coefficients in the characteristic polynomial of a matrix within roundoff error of A. This is true even if the eigenvalues of A are badly conditioned. The traditional algorithms for obtaining the characteristic polynomial, which do not use the eigenvalues, do not have such satisfactory numerical properties.

See Also conv, polyval, residue, roots

polyarea

Purpose	Area of polygon			
Syntax	A = polyarea(X,Y) A = polyarea(X,Y,dim)			
Description	 A = polyarea(X,Y) returns the area of the polygon specified by the vertices in the vectors X and Y. If X and Y are matrices of the same size, then polyarea returns the are of polygons defined by the columns X and Y. If X and Y are multidimensional arrays, polyarea returns the area of the polygons in the first nonsingleton dimension of X and Y. 			
	A = polyarea(X,Y,dim) operates along the dimension specified by scalar dim.			
Examples	L = linspace(0,2.*pi,6); xv = cos(L)';yv = sin(L)'; xv = [xv ; xv(1)]; yv = [yv ; yv(1)]; A = polyarea(xv,yv); plot(xv,yv); title(['Area = ' num2str(A)]); axis image			





convhull, inpolygon, rectint

polyder

Purpose	Polynomial derivative			
Syntax	k = polyder(p) k = polyder(a,b) [q,d] = polyder(b,a)			
Description	The polyder function calculates the derivative of polynomials, polynomial products, and polynomial quotients. The operands a, b, and p are vectors whose elements are the coefficients of a polynomial in descending powers.			
	<pre>k = polyder(p) returns the derivative of the polynomial p.</pre>			
	<pre>k = polyder(a,b) returns the derivative of the product of the polynomials a and b.</pre>			
	[q,d] = polyder(b,a) returns the numerator q and denominator d of the derivative of the polynomial quotient b/a .			
Examples	The derivative of the product $(3x^2 + 6x + 9)(x^2 + 2x)$			
	is obtained with			
	a = [3 6 9]; b = [1 2 0]; k = polyder(a,b) k = 12 36 42 18			
	This result represents the polynomial			
	$12x^3 + 36x^2 + 42x + 18$			
See Also	conv, deconv			

Purpose	Polynomial eigenvalue problem		
Syntax	<pre>[X,e] = polyeig(A0,A1,Ap) e = polyeig(A0,A1,,Ap) [X, e, s] = polyeig(A0,A1,,AP)</pre>		
Description	[X,e] = polyeig(A0,A1,Ap) solves the polynomial eigenvalue problem of degree p		
	$(A_0 + \lambda A_1 + \dots + \lambda^P A_p)x = 0$		
	where polynomial degree p is a non-negative integer, and A0,A1,Ap are input matrices of order n. The output consists of a matrix X of size n -by- $n*p$ whose columns are the eigenvectors, and a vector e of length $n*p$ containing the eigenvalues.		
	If lambda is the jth eigenvalue in e, and x is the jth column of eigenvectors in X, then $(AO + lambda*A1 + + lambda^p*Ap)*x$ is approximately O.		
	e = polyeig(A0,A1,,Ap) is a vector of length n*p whose elements are the eigenvalues of the polynomial eigenvalue problem.		
	[X, e, s] = polyeig(A0, A1,, AP) also returns a vector s of length p*n containing condition numbers for the eigenvalues. At least one of A0 and AP must be nonsingular. Large condition numbers imply that the problem is close to a problem with multiple eigenvalues.		
Remarks	Based on the values of p and n, polyeig handles several special cases:		
	• p = 0, or polyeig(A) is the standard eigenvalue problem: eig(A).		
	 p = 1, or polyeig(A,B) is the generalized eigenvalue problem: eig(A,-B). 		
	 n = 1, or polyeig(a0,a1,ap) for scalars a0, a1, ap is the standard polynomial problem: roots([ap a1 a0]). 		

	If both AO and Ap are singular the problem is potentially ill-posed. Theoretically, the solutions might not exist or might not be unique. Computationally, the computed solutions might be inaccurate. If one, but not both, of AO and Ap is singular, the problem is well posed, but some of the eigenvalues might be zero or infinite.
	Note that scaling AO,A1,,Ap to have norm(Ai) roughly equal 1 may increase the accuracy of polyeig. In general, however, this cannot be achieved. (See Tisseur [3] for more detail.)
Algorithm	The polyeig function uses the QZ factorization to find intermediate results in the computation of generalized eigenvalues. It uses these intermediate results to determine if the eigenvalues are well-determined. See the descriptions of eig and qz for more on this.
See Also	condeig, eig, qz
References	[1] Dedieu, Jean-Pierre Dedieu and Francoise Tisseur, "Perturbation theory for homogeneous polynomial eigenvalue problems," <i>Linear</i> <i>Algebra Appl.</i> , Vol. 358, pp. 71-94, 2003.
	[2] Tisseur, Francoise and Karl Meerbergen, "The quadratic eigenvalue problem," <i>SIAM Rev.</i> , Vol. 43, Number 2, pp. 235-286, 2001.
	[3] Francoise Tisseur, "Backward error and condition of polynomial eigenvalue problems" <i>Linear Algebra Appl.</i> , Vol. 309, pp. 339-361, 2000.

Purpose	Polynomial curve fitting
---------	--------------------------

Syntax p = polyfit(x,y,n)
[p,S] = polyfit(x,y,n)
[p,S,mu] = polyfit(x,y,n)

Description p = polyfit(x,y,n) finds the coefficients of a polynomial p(x) of degree n that fits the data, p(x(i)) to y(i), in a least squares sense. The result p is a row vector of length n+1 containing the polynomial coefficients in descending powers:

$$p(x) = p_1 x^n + p_2 x^{n-1} + \dots + p_n x + p_{n+1}$$

[p,S] = polyfit(x,y,n) returns the polynomial coefficients p and a structure S for use with polyval to obtain error estimates or predictions. Structure S contains fields R, df, and normr, for the triangular factor from a QR decomposition of the Vandermonde matrix of x, the degrees of freedom, and the norm of the residuals, respectively. If the data y are random, an estimate of the covariance matrix of p is (Rinv*Rinv')*normr^2/df, where Rinv is the inverse of R. If the errors in the data y are independent normal with constant variance, polyval produces error bounds that contain at least 50% of the predictions.

[p,S,mu] = polyfit(x,y,n) finds the coefficients of a polynomial in

$$\hat{x} = \frac{x - \mu_1}{\mu_2}$$

where $\mu_1 = \text{mean}(x)$ and $\mu_2 = \text{std}(x)$. mu is the two-element vector $[\mu_1,\mu_2]$. This centering and scaling transformation improves the numerical properties of both the polynomial and the fitting algorithm.

Examples This example involves fitting the error function, erf(x), by a polynomial in x. This is a risky project because erf(x) is a bounded function, while polynomials are unbounded, so the fit might not be very good.

First generate a vector of x points, equally spaced in the interval [0, 2.5]; then evaluate erf(x) at those points.

```
x = (0: 0.1: 2.5)';
y = erf(x);
```

The coefficients in the approximating polynomial of degree 6 are

```
p = polyfit(x,y,6)
p =
0.0084 -0.0983 0.4217 -0.7435 0.1471 1.1064 0.0004
```

There are seven coefficients and the polynomial is

 $.0084x^6 - 0.0983x^5 + 0.4217x^3 + 0.1471x^2 + 1.106x + 0.0004$. To see how good the fit is, evaluate the polynomial at the data points with:

f = polyval(p,x);

A table showing the data, fit, and error is


```
table = [x y f y-f]
```

table =

0	0	0.0004	-0.0004
0.1000	0.1125	0.1119	0.0006
0.2000	0.2227	0.2223	0.0004
0.3000	0.3286	0.3287	-0.0001
0.4000	0.4284	0.4288	-0.0004
2.1000	0.9970	0.9969	0.0001
2.2000	0.9981	0.9982	-0.0001
2.3000	0.9989	0.9991	-0.0003
2.4000	0.9993	0.9995	-0.0002
2.5000	0.9996	0.9994	0.0002

So, on this interval, the fit is good to between three and four digits. Beyond this interval the graph shows that the polynomial behavior takes over and the approximation quickly deteriorates.

```
x = (0: 0.1: 5)';
y = erf(x);
f = polyval(p,x);
plot(x,y,'o',x,f,'-')
axis([0 5 0 2])
```



Algorithm The polyfit MATLAB file forms the Vandermonde matrix, V, whose elements are powers of x. $v_{i,j} = x_i^{n-j}$

It then uses the backslash operator, \, to solve the least squares problem $Vp \cong y$.

You can modify the MATLAB file to use other functions of x as the basis functions.

See Also poly, polyval, roots, lscov, cov

Purpose	Integrate polynomial analytically		
Syntax	<pre>polyint(p,k) polyint(p)</pre>		
Description	<pre>polyint(p,k) returns a polynomial representing the integral of polynomial p, using a scalar constant of integration k. polyint(p) assumes a constant of integration k=0.</pre>		
See Also	polyder, polyval, polyvalm, polyfit		

polyval

Purpose	Polynomial evaluation		
Syntax	y = polyval(p,x) [y,delta] = polyval(p,x,S) y = polyval(p,x,[],mu) [y,delta] = polyval(p,x,S,mu)		
Description	y = polyval(p,x) returns the value of a polynomial of degree n evaluated at x. The input argument p is a vector of length n+1 whose elements are the coefficients in descending powers of the polynomial to be evaluated.		
	$y = p_1 x^n + p_2 x^{n-1} + \ldots + p_n x + p_{n+1}$		
	x can be a matrix or a vector. In either case, polyval evaluates p at each element of x.		
	[y,delta] = polyval(p,x,S) uses the optional output structure S generated by polyfit to generate error estimates delta. delta is an estimate of the standard deviation of the error in predicting a future observation at x by $p(x)$. If the coefficients in p are least squares estimates computed by polyfit, and the errors in the data input to polyfit are independent, normal, and have constant variance, then y±delta contains at least 50% of the predictions of future observations at x.		
	<pre>y = polyval(p,x,[],mu) or [y,delta] = polyval(p,x,S,mu) use</pre>		
	$\hat{x} = (x - \mu_1) / \mu_2$ in place of x. In this equation, $\mu_1 = \text{mean}(x)$ and		
	$\mu_2=\mathrm{std}(x)$. The centering and scaling parameters $\mathrm{mu}=[\mu_1,\mu_2]$ are optional output computed by <code>polyfit</code> .		
Remarks	The $polyvalm(p,x)$ function, with x a matrix, evaluates the polynomial in a matrix sense. See $polyvalm$ for more information.		

Examples	The polynomial $p(x) = 3x^2 + 2x + 1$ is evaluated at $x = 5$, 7, and 9 with				
	p = [3 2 1]; polyval(p,[5 7 9])				
	which results in				
	ans =				
	86 162 262				
	For another example, see polyfit.				
See Also	polyfit, polyvalm, polyder, polyint				

polyvalm

Purpose	Matrix polynomial evaluation			
Syntax	Y = polyvalm(p,X)			
Description	Y = polyvalm(p,X) evaluates a polynomial in a matrix sense. This is the same as substituting matrix X in the polynomial p.			
	Polynomial p is a vector whose elements are the coefficients of a polynomial in descending powers, and X must be a square matrix.			
Examples	The Pascal matrices are formed from Pascal's triangle of binomial coefficients. Here is the Pascal matrix of order 4.			
	X = pascal(4)			
	X =			
	1 1 1 1 1 2 3 4 1 3 6 10			
	1 2 3 4			
	1 3 6 10			
	1 4 10 20			

Its characteristic polynomial can be generated with the poly function.

p = poly(X) p = 1 -29 72 -29 1

This represents the polynomial $x^4 - 29x^3 + 72x^2 - 29x + 1$.

Pascal matrices have the curious property that the vector of coefficients of the characteristic polynomial is palindromic; it is the same forward and backward.

Evaluating this polynomial at each element is not very interesting.

polyval(p,X)			
ans =			
16	16	16	16
16	15	- 140	-563
16	-140	-2549	-12089

16 -563 -12089 -43779

But evaluating it in a matrix sense is interesting.

polyva	lm(p,	X)	
ans =			
0	0	0	0
0	0	0	0
0	0	0	0
0	0	0	0

The result is the zero matrix. This is an instance of the Cayley-Hamilton theorem: a matrix satisfies its own characteristic equation.

See Also polyfit, polyval

Purpose	Base 2 power and scale floating-point numbers			
Syntax	X = pow2(Y) X = pow2(F,E)			
Description	X = pow2(Y) returns an array X whose elements are 2 raised to the power Y.			
	X = pow2(F,E) computes $x = f * 2^e$ for corresponding elements of F and E. The result is computed quickly by simply adding E to the floating-point exponent of F. Arguments F and E are real and integer arrays, respectively.			
Remarks	This function corresponds to the ANSI C function $ldexp()$ and the IEEE floating-point standard function $scalbn()$.			
Examples	For IEEE arithmetic, the statement $X = pow2(F,E)$ yields the values:			
	F	E	Х	
	1/2		1	
	pi/4	2	pi	
	-3/4		-3	
	1/2 -51 eps 1-eps/2 1024 realmax			
	1/2		realmin	
See Also	log2, exp, hex2num, realmax, realmin			
	The arithmetic operators ^ and .^			

Purpose	Array power
Syntax	$Z = X.^{Y}$
Description	$Z = X.^Y$ denotes element-by-element powers. X and Y must have the same dimensions unless one is a scalar. A scalar is expanded to an array of the same size as the other input.
	C = power(A,B) is called for the syntax 'A .^ B' when A or B is an object.
	Note that for a negative value X and a non-integer value Y, if the $abs(Y)$ is less than one, the power function returns the complex roots. To obtain the remaining real roots, use the nthroot function.
See Also	nthroot, realpow

ppval

Purpose	Evaluate piecewise polynomial		
Syntax	v = ppval(pp,xx)		
Description	v = ppval(pp,xx) returns the value of the piecewise polynomial f , contained in pp, at the entries of xx. You can construct pp using the functions interp1, pchip, spline, or the spline utility mkpp.		
	v is obtained by replacing each entry of xx by the value of <i>f</i> there. If <i>f</i> is scalar-valued, v is of the same size as xx. xx may be N-dimensional.		
	If pp was constructed by pchip, spline, or mkpp using the orientation of non-scalar function values specified for those functions, then:		
	If f is $[D1,,Dr]$ -valued, and xx is a vector of length N, then V has size $[D1,,Dr, N]$, with V(:,,:,J) the value of f at xx(J).		
	If f is $[D1,, Dr]$ -valued, and xx has size $[N1,, Ns]$, then V has size $[D1,, Dr, N1,, Ns]$, with V(:,,:, J1,, Js) the value of f at xx(J1,, Js).		
	If pp was constructed by interp1 using the orienatation of non-scalar function values specified for that function, then:		
	If f is [D1,,Dr]-valued, and xx is a vector of length N, then V has size [N,D1,,Dr], with V(J,:,,:) the value of f at xx(J).		
	If f is $[D1,, Dr]$ -valued, and xx has size $[N1,, Ns]$, then V has size $[N1,, Ns, D1,, Dr]$, with $V(J1,, Js, :,, :)$ the value of f at xx(J1,, Js).		
Examples	Compare the results of integrating the function cos		
	a = 0; b = 10; int1 = quad(@cos,a,b)		
	int1 = -0.5440		

with the results of integrating the piecewise polynomial pp that approximates the cosine function by interpolating the computed values x and y.

```
x = a:b;
y = cos(x);
pp = spline(x,y);
int2 = quad(@(x)ppval(pp,x),a,b)
int2 =
    -0.5485
```

int1 provides the integral of the cosine function over the interval
[a,b], while int2 provides the integral over the same interval of the
piecewise polynomial pp.

See Also mkpp, spline, unmkpp

prefdir

Purpose	Folder containing preferences, history, and layout files		
Syntax	prefdir f = prefdir f = prefdir(1)		
Description	prefdir returns the folder that contains		
	 Preferences for MATLAB and related products (matlab.prf) 		
	• Command history file (history.m)		
	• MATLAB shortcuts (shortcuts.xml)		
	 MATLAB desktop layout files (MATLABDesktop.xml and Your_Saved_LayoutMATLABLayout.xml) 		
	• Other related files		
	<pre>f = prefdir assigns to f the name of the folder containing preferences and related files.</pre>		
	f = prefdir(1) creates a folder for preferences and related files if one does not exist. If the folder does exist, the name is assigned to f .		
Remarks	You must have write access to the preferences folder, or MATLAB generates an error in the Command Window when you try to change preferences.		
	The folder might be a hidden folder, for example, myname/.matlab/R2009a. For more information, see "Viewing Hidden Files and Folders".		
	The preferences folder MATLAB uses and how preferences migrate when you use a new version of MATLAB depend on the version. In R14SP3, there was a change to the way that the preference folders were named and how they migrated, affecting R13 through R14SP2. The differences are relevant if you run multiple versions of MATLAB and one version is prior to R14SP3:		

• For R2009b back through and including R2006a, and R14SP3, MATLAB uses the name of the release for the preference folder. For example, R2009b, R2009a, ... through R14SP3. When you install R2009b, MATLAB migrates the files in the R2009a preferences folder to the R2009b preferences folder. While running R2009b through R14SP3, any changes made to files in those preferences folders (R2009b through R14SP3) are used only in their respective versions. As an example, commands you run in R2009b will *not* appear in the Command History when you run R2009a, and so on. The converse is also true.

Upon startup, MATLAB 7.9 (R2009b) looks for, and if found uses, the R2009b preferences folder. If not found, MATLAB creates an R2009b preferences folder. This happens when the R2009b preferences folder is deleted or does not exist for some other reason. MATLAB then looks for the R2009a preferences folder, and if found, migrates the R2009a preferences to the R2009b preferences. If it does not find the R2009a preferences folder, it uses the default preferences for R2009b. This process also applies when starting MATLAB 7.8 (R2009a) through 7.1 (R14SP3).

If you want to use default preferences for R2009b, and do not want MATLAB to migrate preferences from R2009a, the R2009b preferences folder *must exist but be empty* when you start MATLAB. If you want to maintain some of your R2009b customizations, but restore the defaults for others, in the R2009b preferences folder, delete the files for which you want the defaults to be restored. One file you might want to maintain is history.m—for more information about the file, see "Viewing Statements in the Command History Window" in the MATLAB Desktop Tools and Development Environment documentation.

• The R14 through R14SP2 releases all share the R14 preferences folder. While running R14SP1, for example, any changes made to files in the preferences folder, R14, are used when you run R14SP2 and R14. As another example, commands you run in R14 appear in the Command History when you run R14SP2, and the converse is also true. The preferences are not used when you run R14SP3 or

later versions because those versions each use their own preferences folders. • All R13 releases use the R13 preferences folder. While running R13SP1, for example, any changes made to files in the preferences folder, R13, are used when you run R13. As an example, commands you run in R13 will appear in the Command History when you run R13SP1, and the converse is true. The preferences are not used when you run any R14 or later releases because R14 and later releases use different preferences folders, and the converse is true. **Examples** View the location of the preferences folder: prefdir MATLAB returns: ans = C:\WINNT\Profiles\my user name\MATHWORKS\Application Data\MathWorks\MATLAB\R2009a Run dir for the folder to see the files for customizing MathWorks products: history.m . matlab.prf . . cwdhistory.m MATLABDesktop.xml shortcuts.xml MATLAB EditorDesktop.xml . . . In MATLAB, run cd(prefdir) to make the preferences folder become the current folder. On Windows platforms, go directly to the preferences folder in Microsoft Windows Explorer by running winopen(prefdir). See Also preferences, winopen

"Specifying Options for MATLAB Using Preferences" in the MATLAB Desktop Tools and Development Environment documentation

preferences

Purpose	Open Preferences dialog box
GUI Alternatives	As an alternative to the preferences function, select File > Preferences in the MATLAB desktop or any desktop tool.
Syntax	preferences
Description	preferences displays the Preferences dialog box, from which you can make changes to options for MATLAB and related products.
See Also	prefdir
	"Specifying Options for MATLAB Using Preferences" in the MATLAB Desktop Tools and Development Environment documentation

Purpose	Generate list of prime numbers			
Syntax	<pre>p = primes(n)</pre>			
Description	p = primes(n) returns a row vector of the prime numbers less than or equal to n. A prime number is one that has no factors other than 1 and itself.			
Examples	p = primes(37)			
	p = 2 3 5 7 11 13 17 19 23 29 31 37			
See Also	factor			

Purpose	Print figure or save to file and configure printer defaults		
	Contents		
	"GUI Alternative" on page 2-3072		
	"Syntax"		
	"Description" on page 2-3072		
	"Printer Drivers" on page 2-3074		
	"Graphics Format Files" on page 2-3079		
	"Printing Options" on page 2-3083		
	"Paper Sizes" on page 2-3086		
	"Printing Tips" on page 2-3087		
	"Examples" on page 2-3090		
	"See Also" on page 2-3092		
GUI Alternative	Select File > Print from the figure window to open the Print dialog box and File > Print Preview to open the Print Preview GUI. For details, see "How to Print or Export" in the MATLAB Graphics documentation.		
Syntax	print print('argument1','argument2',) print(handle,'filename') print argument1 argument2 argumentn [pcmd,dev] = printopt		
Description	print and printopt produce hard-copy output. All arguments to the print command are optional. You can use them in any combination or order.		
	print sends the contents of the current figure, including bitmap representations of any user interface controls, to the printer using the device and system printing command defined by printopt.		

print('argument1', 'argument2',...) is the function form of print. It enables you to pass variables for any input arguments. This form is useful for passing file names and handles (for example, print(handle, 'filename'). See "Batch Processing" on page 2-3091 for an example. Also see "Specifying the Figure to Print" on page 2-3090 for further examples.

print argument1 argument2 ... argumentn prints the figure using the specified arguments.

The following arguments apply to both the function and the command form:

Argument	Description
handle	Print the specified object.
filename	Direct the output to the PostScript file designated by filename. If filename does not include an extension, print appends an appropriate extension.
-ddriver	Print the figure using the specified printer <i>driver</i> , (such as color PostScript). If you omit - <i>ddriver</i> , print uses the default value stored in printopt.m. The table in "Printer Drivers" on page 2-3074 lists all supported device types.
-dformat	Copy the figure to the system Clipboard (Microsoft Windows platforms only). To be valid, the <i>format</i> for this operation must be either -dmeta (Windows Enhanced Metafile) or -dbitmap (Windows Bitmap).
-d <i>format</i> filename	Export the figure to the specified file using the specified graphics <i>format</i> (such as TIFF). The table of "Graphics Format Files" on page 2-3079 lists all supported graphics file formats.

Argument	Description
-smodelname	Print the current Simulink model modelname.
-options	Specify print options that modify the action of the print command. (For example, the -noui option suppresses printing of user interface controls.) "Printing Options" on page 2-3083 lists available options.

[pcmd,dev] = printopt returns strings containing the current system-dependent printing command and output device. printopt is a file used by print to produce the hard-copy output. You can edit the file printopt.m to set your default printer type and destination.

pcmd and dev are platform-dependent strings. pcmd contains the command that print uses to send a file to the printer. dev contains the printer driver or graphics format option for the print command. Their defaults are platform dependent.

Platform	Print Command	Driver or Format
Mac and UNIX	lpr -r	-dps2
Windows	COPY /B %s LPT1:	-dwin

Printer Drivers

The following table shows the more widely used printer drivers supported by MATLAB software. If you do not specify a driver, the default setting shown in the previous table is used. For a list of all supported printer drivers, type print -d at the MATLAB prompt. Some things to remember:

- As indicated in "Description" on page 2-3072 the -d switch specifies a printer driver or a graphics file format:
 - Specifying a printer driver without a file name or printer name (the -P option) sends the output formatted by the specified driver to your default printer, which may not be what you want to do.

Note On Windows systems, when you use the -P option to identify a printer to use, if you specify any driver other than -dwin or -dwinc, MATLAB writes the output to a file with an appropriate extension but does not send it to the printer. You can then copy that file to a printer.

- Specifying a -dmeta or a -dbitmap graphics format without a file name places the graphic on the system Clipboard, if possible (Windows platforms only).
- Specifying any other graphics format without a file name creates a file in the current folder with a name such as figureN.fmt, where N is 1, 2, 3, ... and fmt indicates the format type, for example, eps or png.
- Several drivers come from a product called Ghostscript, which is shipped with MATLAB software. The last column indicates when Ghostscript is used.
- Not all drivers are supported on all platforms. Non support is noted in the first column of the table.
- If you specify a particular printer with the -P option and do not specify a driver, a default driver for that printer is selected, either by the operating system or by MATLAB, depending on the platform:
 - On Windows, the driver associated with this particular printing device is used.
 - On Macintosh and UNIX platforms, the driver specified in printopt.m is used

See Selecting the Printer in the Graphics documentation for more information.

Note The MathWorks[™] is planning to leverage existing operating system (OS) support for printer drivers and devices. As a result, the ability to specify certain print devices using the print -d command, and certain graphics formats using the print -d command and/or the saveas command, will be removed in a future release. In the following table, the affected formats have an asterisk (*) next to the print command option string. The asterisks provide a link to the Web site which supplies a form for users to give feedback about these changes.

Printer Driver	Print Command Option String	Ghostscript
Canon BubbleJet BJ10e	-dbj10e *	Yes
Canon BubbleJet BJ200 color	-dbj200 *	Yes
Canon Color BubbleJet BJC-70/BJC-600/BJC-400	-dbjc600 * 0	Yes
Canon Color BubbleJet BJC-800	-dbjc800 *	Yes
Epson and compatible 9- or 24-pin dot matrix print drivers	-depson *	Yes
Epson and compatible 9-pin with interleaved lines (triple resolution)	-deps9high *	Yes
Epson LQ-2550 and compatible; color (not supported on HP-700)	-depsonc *	Yes
Fujitsu 3400/2400/1200	-depsonc *	Yes

Printer Driver	Print Command Option String	Ghostscript
HP DesignJet 650C color (not supported on Windows)	-ddnj650c *	Yes
HP DeskJet 500	-ddjet500 *	Yes
HP DeskJet 500C (creates black and white output)	-dcdjmono *	Yes
HP DeskJet 500C (with 24 bit/pixel color and high-quality Floyd-Steinberg color dithering) (not supported on Windows)	-dcdjcolor *	Yes
HP DeskJet 500C/540C color (not supported on Windows)	-dcdj500 *	Yes
HP Deskjet 550C color (not supported on Windows)	-dcdj550 *	Yes
HP DeskJet and DeskJet Plus	-ddeskjet *	Yes
HP LaserJet	-dlaserjet *	Yes
HP LaserJet+	-dljetplus *	Yes
HP LaserJet IIP	-dljet2p *	Yes
HP LaserJet III	-dljet3 *	Yes
HP LaserJet 4, 5L and 5P	-dljet4 *	Yes
HP LaserJet 5 and 6	-dpxlmono *	Yes

Printer Driver	Print Command Option String	Ghostscript
HP PaintJet color	-dpaintjet *	Yes
HP PaintJet XL color	-dpjxl *	Yes
HP PaintJet XL color	-dpjetxl *	Yes
HP PaintJet XL300 color (not supported on Windows)	-dpjx1300 *	Yes
HPGL for HP 7475A and other compatible plotters. (Renderer cannot be set to Z-buffer.)	-dhpgl *	No
IBM 9-pin Proprinter	-dibmpro *	Yes
PostScript black and white	-dps	No
PostScript color	-dpsc	No
PostScript Level 2 black and white	-dps2	No
PostScript Level 2 color	-dpsc2	No
Windows color (Windows only)	-dwinc	No
Windows monochrome (Windows only)	-dwin	No

Tip Generally, Level 2 PostScript files are smaller and are rendered more quickly when printing than Level 1 PostScript files. However, not all PostScript printers support Level 2, so determine the capabilities of your printer before using those drivers. Level 2 PostScript printing is the default for UNIX platforms. You can change this default by editing the printopt.m file. Likewise, if you want color PostScript printing to be the default instead of black-and-white PostScript printing, edit the line in the printopt.m file that reads dev = '-dps2'; to be dev = '-dpsc2';.

Graphics Format Files

To save your figure as a graphics format file, specify a format switch and file name. To set the resolution of the output file for a built-in MATLAB format, use the -r switch. (For example, -r300 sets the output resolution to 300 dots per inch.) The -r switch is also supported for Windows Enhanced Metafiles, JPEG, TIFF and PNG files, but is not supported for Ghostscript raster formats. For more information, see "Printing and Exporting without a Display" on page 2-3082 and "Resolution Considerations" on page 2-3085.

Note When you print to a file, the file name must have fewer than 128 characters, including path name. When you print to a file in your current folder, the filename must have fewer than 126 characters, because MATLAB places './' or '.\'' at the beginning of the filename when referring to it.

The following table shows the supported output formats for exporting from figures and the switch settings to use. In some cases, a format is available both as a MATLAB output filter and as a Ghostscript output filter. All formats except for EMF are supported on both PC and UNIX platforms.

Graphics Format	Bitmap or Vector	Print Command Option String	MATLAB or Ghostscript
BMP monochrome BMP	Bitmap	-dbmpmono	Ghostscript
BMP 24-bit BMP	Bitmap	-dbmp16m	Ghostscript
BMP 8-bit (256-color) BMP (this format uses a fixed colormap)	Bitmap	-dbmp256	Ghostscript
BMP 24-bit	Bitmap	-dbmp	MATLAB
EMF	Vector	-dmeta	MATLAB
EPS black and white	Vector	-deps	MATLAB
EPS color	Vector	-depsc	MATLAB
EPS Level 2 black and white	Vector	-deps2	MATLAB
EPS Level 2 color	Vector	-depsc2	MATLAB
HDF 24-bit	Bitmap	-dhdf	MATLAB
ILL (Adobe Illustrator)	Vector	-dill	MATLAB
JPEG 24-bit	Bitmap	-djpeg	MATLAB
PBM (plain format) 1-bit	Bitmap	-dpbm	Ghostscript
PBM (raw format) 1-bit	Bitmap	-dpbmraw	Ghostscript
PCX 1-bit	Bitmap	-dpcxmono	Ghostscript

Graphics Format	Bitmap or Vector	Print Command Option String	MATLAB or Ghostscript
PCX 24-bit color PCX file format, three 8-bit planes	Bitmap	-dpcx24b	Ghostscript
PCX 8-bit newer color PCX file format (256-color)	Bitmap	-dpcx256	Ghostscript
PCX Older color PCX file format (EGA/VGA, 16-color)	Bitmap	-dpcx16	Ghostscript
PDF Color PDF file format	Vector	-dpdf	Ghostscript
PGM Portable Graymap (plain format)	Bitmap	-dpgm	Ghostscript
PGM Portable Graymap (raw format)	Bitmap	-dpgmraw	Ghostscript
PNG 24-bit	Bitmap	-dpng	MATLAB
PPM Portable Pixmap (plain format)	Bitmap	-dppm	Ghostscript
PPM Portable Pixmap (raw format)	Bitmap	-dppmraw	Ghostscript
SVG Scalable Vector Graphics	Vector	-dsvg	MATLAB

Graphics Format	Bitmap or Vector	Print Command Option String	MATLAB or Ghostscript
TIFF 24-bit	Bitmap	-dtiff or -dtiffn	MATLAB
TIFF preview for EPS files	Bitmap	-tiff	

The TIFF image format is supported on all platforms by almost all word processors for importing images. The -dtiffn variant writes an uncompressed TIFF. JPEG is a lossy, highly compressed format that is supported on all platforms for image processing and for inclusion into HTML documents on the Web. To create these formats, MATLAB renders the figure using the Z-buffer rendering method and the resulting bitmap is then saved to the specified file.

Printing and Exporting without a Display

On a UNIX platform (including Macintosh), where you can start in MATLAB nodisplay mode (matlab -nodisplay), you can print using most of the drivers you can use with a display and export to most of the same file formats. The PostScript and Ghostscript devices all function in nodisplay mode on UNIX platforms. The graphic devices -djpeg, -dpng, -dtiff (compressed TIFF bitmaps), and -tiff (EPS with TIFF preview) work as well, but under nodisplay they use Ghostscript to generate output instead of using the drivers built into MATLAB. However, Ghostscript ignores the -r option when generating -djpeg, -dpng, -dtiff, and -tiff image files. This means that you cannot vary the resolution of image files when running in nodisplay mode.

Naturally, the Windows only -dwin and -dwinc output formats cannot be used on UNIX or Mac platforms with or without a display.

The same holds true on Windows platforms with the -noFigureWindows startup option. The -dwin, -dwinc, and -dsetup options operate as usual under -noFigureWindows. However, the printpreview GUI does not function in this mode.

The formats which you cannot generate in nodisplay mode on UNIX and Mac platforms are:

- bitmap (-dbitmap) Windows bitmap file (except for Simulink models)
- bmp (-dbmp...) Monochrome and color bitmaps
- hdf (-dhdf) Hierarchical Data Format
- svg (-dsvg) Scalable Vector Graphics file (except for Simulink models)
- tiffn (-dtiffn) TIFF image file, no compression

In addition, uicontrols do not print or export in nodisplay mode.

Printing Options

This table summarizes options that you can specify for print. The second column links to tutorials in "Printing and Exporting" in the MATLAB Graphics documentation that provide operational details. Also see "Resolution Considerations" on page 2-3085 for information on controlling output resolution.

Option	Description
-adobecset	PostScript devices only. Use PostScript default character set encoding. See "Early PostScript 1 Printers".
-append	PostScript devices only. Append figure to existing PostScript file. See "Settings That Are Driver Specific".
-cmyk	PostScript devices only. Print with CMYK colors instead of RGB. See "Setting CMYK Color".
-ddriver	Printing only. Printer driver to use. See "Printer Drivers" on page 2-3074 table.
-dformat	Exporting only. Graphics format to use. See "Graphics Format Files" table.

Option	Description
-dsetup	Windows printing only. Display the (platform-specific) Print Setup dialog. Settings you make in it are saved, but nothing is printed.
-fhandle	Handle of figure to print. Note that you cannot specify both this option and the <i>-swindowtitle</i> option. See "Which Figure Is Printed".
-loose	PostScript and Ghostscript printing only. Use loose bounding box for PostScript output. See "Producing Uncropped Figures".
-noui	Suppress printing of user interface controls. See "Excluding User Interface Controls".
-opengl	Render using the OpenGL algorithm. Note that you cannot specify this method in conjunction with -zbuffer or -painters. See "Selecting a Renderer".
-painters	Render using the Painter's algorithm. Note that you cannot specify this method in conjunction with -zbuffer or -opengl. See "Selecting a Renderer".
-Pprinter	Specify name of printer to use. See "Selecting the Printer".
-rnumber	PostScript and built-in raster formats, and Ghostscript vector format only. Specify resolution in dots per inch. Defaults to 90 for Simulink, 150 for figures in image formats and when printing in Z-buffer or OpenGL mode, screen resolution for metafiles, and 864 otherwise. Use -r0 to specify screen resolution. For details, see "Resolution Considerations" on page 2-3085 and "Setting the Resolution".

Option	Description
-swindowtitle	Specify name of Simulink system window to print. Note that you cannot specify both this option and the <i>-fhandle</i> option. See "Which Figure Is Printed".
- V	Windows printing only. Display the Windows Print dialog box. The v stands for "verbose mode."
-zbuffer	Render using the Z-buffer algorithm. Note that you cannot specify this method in conjunction with -opengl or -painters. See "Selecting a Renderer".

Resolution Considerations

Use -rnumber to specify the resolution of the generated output. In general, using a higher value will yield higher quality output but at the cost of larger output files. It affects the resolution and output size of all MATLAB built-in *raster* formats (which are identified in column four of the table in "Graphics Format Files" on page 2-3079).

Note Built-in graphics formats are generated directly from MATLAB without conversion through the Ghostscript library. Also, in headless (nodisplay) mode, writing to certain image formats is not done by built-in drivers, as it is when a display is being used. These formats are -djpeg, -dtiff, and -dpng. Furthermore, the -dhdf and -dbmp formats cannot be generated in headless mode (but you can substitute -dbmp16m for -dbmp). See "Printing and Exporting without a Display" on page 2-3082 for details on printing when not using a display.

Unlike the built-in MATLAB formats, graphic output generated via Ghostscript does not directly obey -r option settings. However, the intermediate PostScript file generated by MATLAB as input for the Ghostscript processor is affected by the -r setting and thus can indirectly influence the quality of the final Ghostscript generated output.

The effect of the -r option on output quality can be subtle at ordinary magnification when using the OpenGL or ZBuffer renderers and writing to one of the MATLAB built-in raster formats, or when generating vector output that contains an embedded raster image (for example, PostScript or PDF). The effect of specifying higher resolution is more apparent when viewing the output at higher magnification or when printed, since a larger -r setting provides more data to use when scaling the image.

When generating fully vectorized output (as when using the Painters renderer to output a vector format such as PostScript or PDF), the resolution setting affects the degree of detail of the output; setting resolution higher generates crisper output (but small changes in the resolution may have no observable effect). For example, the gap widths of lines that do not use a solid ('-') linestyle can be affected.

Paper Sizes

MATLAB printing supports a number of standard paper sizes. You can select from the following list by setting the PaperType property of the figure or selecting a supported paper size from the Print dialog box.

Property Value	Size (Width by Height)
usletter	8.5 by 11 inches
uslegal	8.5 by 14 inches
tabloid	11 by 17 inches
A0	841 by 1189 mm
A1	594 by 841 mm
A2	420 by 594 mm
A3	297 by 420 mm
A4	210 by 297 mm
A5	148 by 210 mm
во	1029 by 1456 mm

Property Value	Size (Width by Height)
B1	728 by 1028 mm
B2	514 by 728 mm
В3	364 by 514 mm
B4	257 by 364 mm
B5	182 by 257 mm
arch-A	9 by 12 inches
arch-B	12 by 18 inches
arch-C	18 by 24 inches
arch-D	24 by 36 inches
arch-E	36 by 48 inches
A	8.5 by 11 inches
В	11 by 17 inches
C	17 by 22 inches
D	22 by 34 inches
E	34 by 43 inches

Printing

Figures with Resize Functions

Tips

The print command produces a warning when you print a figure having a callback routine defined for the figure ResizeFcn. To avoid the warning, set the figure PaperPositionModeproperty to auto or select Match Figure Screen Size in the File > Page Setup dialog box.

Troubleshooting Microsoft Windows Printing

If you encounter problems such as segmentation violations, general protection faults, or application errors, or the output does not appear as you expect when using Microsoft printer drivers, try the following:

- If your printer is PostScript compatible, print with one of the MATLAB built-in PostScript drivers. There are various PostScript device options that you can use with print, which all start with -dps.
- The behavior you are experiencing might occur only with certain versions of the print driver. Contact the print driver vendor for information on how to obtain and install a different driver.
- Try printing with one of the MATLAB built-in Ghostscript devices. These devices use Ghostscript to convert PostScript files into other formats, such as HP LaserJet, PCX, Canon BubbleJet, and so on.
- Copy the figure as a Windows Enhanced Metafile using the **Edit** > **Copy Figure** menu item on the figure window menu or the print -dmeta option at the command line. You can then import the file into another application for printing.

You can set copy options in the figure's **File > Preferences > Copying Options** dialog box. The Windows Enhanced Metafile Clipboard format produces a better quality image than Windows Bitmap.

Printing MATLAB GUIs

You can generally obtain better results when printing a figure window that contains MATLAB uicontrols by setting these key properties:

• Set the figure PaperPositionMode property to auto. This ensures that the printed version is the same size as the on-screen version. With PaperPositionMode set to auto MATLAB, does not resize the figure to fit the current value of the PaperPosition. This is particularly important if you have specified a figure ResizeFcn, because if MATLAB resizes the figure during the print operation, ResizeFcn is automatically called.

To set PaperPositionMode on the current figure, use the command:

```
set(gcf, 'PaperPositionMode', 'auto')
```

• Set the figure InvertHardcopy property to off. By default, MATLAB changes the figure background color of printed output to white,

but does not change the color of uicontrols. If you have set the background color, for example, to match the gray of the GUI devices, you must set InvertHardcopy to off to preserve the color scheme.

To set InvertHardcopy on the current figure, use the command:

```
set(gcf,'InvertHardcopy','off')
```

- Use a color device if you want lines and text that are in color on the screen to be written to the output file as colored objects. Black and white devices convert colored lines and text to black or white to provide the best contrast with the background and to avoid dithering.
- Use the print command's -loose option to keep a bounding box from being too tightly wrapped around objects contained in the figure. This is important if you have intentionally used space between uicontrols or axes and the edge of the figure and you want to maintain this appearance in the printed output.

If you print or export in nodisplay mode, none of the uicontrols the figure has will be visible. If you run code that adds uicontrols to a figure when the figure is invisible, the controls will not print until the figure is made visible.

Printing Interpolated Shading with PostScript Drivers

You can print MATLAB surface objects (such as graphs created with surf or mesh) using interpolated colors. However, only patch objects that are composed of triangular faces can be printed using interpolated shading.

Printed output is always interpolated in RGB space, not in the colormap colors. This means that if you are using indexed color and interpolated face coloring, the printed output can look different from what is displayed on screen.

PostScript files generated for interpolated shading contain the color information of the graphics object's vertices and require the printer to perform the interpolation calculations. This can take an excessive amount of time and in some cases, printers might time out before finishing the print job. One solution to this problem is to interpolate the data and generate a greater number of faces, which can then be flat shaded.

To ensure that the printed output matches what you see on the screen, print using the -zbuffer option. To obtain higher resolution (for example, to make text look better), use the -r option to increase the resolution. There is, however, a tradeoff between the resolution and the size of the created PostScript file, which can be quite large at higher resolutions. The default resolution of 150 dpi generally produces good results. You can reduce the size of the output file by making the figure smaller before printing it and setting the figure PaperPositionMode to auto, or by just setting the PaperPosition property to a smaller size.

Examples Specifying the Figure to Print

Pass a figure handle as a variable to the function form of print. For example:

```
h = figure;
plot(1:4,5:8)
print(h)
```

Save the figure with the handle h to a PostScript file named Figure2, which can be printed later:

```
print(h,'-dps','Figure2.ps')
```

Pass in a file name as a variable:

```
filename = 'mydata';
print(h, '-dpsc', filename);
```

(Because a file name is specified, the figure will be printed to a file.)

Specifying the Model to Print

Print a noncurrent Simulink model using the -s option with the title of the window (in this case, f14):

```
print('-sf14')
```

If the window title includes any spaces, you must call the function form rather than the command form of print. For example, this command saves the Simulink window title Thruster Control:

```
print('-sThruster Control')
```

To print the current system, use:

print('-s')

For information about issues specific to printing Simulink windows, see the Simulink documentation.

Printing Figures at Screen Size

This example prints a surface plot with interpolated shading. Setting the current figure's (gcf) PaperPositionMode to auto enables you to resize the figure window and print it at the size you see on the screen. See "Printing Options" on page 2-3083 and "Printing Interpolated Shading with PostScript Drivers" on page 2-3089 for information on the -zbuffer and -r200 options.

```
surf(peaks)
shading interp
set(gcf,'PaperPositionMode','auto')
print('-dpsc2','-zbuffer','-r200')
```

For additional details, see "Printing Images" in the MATLAB Graphics documentation.

Batch Processing

You can use the function form of print to pass variables containing file names. For example, this for loop uses file names stored in a cell array to create a series of graphs and prints each one with a different file name:

```
fnames = {'file1', 'file2', 'file3'};
```

```
for k=1:length(fnames)
    surf(peaks)
    print('-dtiff','-r200',fnames{k})
end
```

Tiff Preview

The command

```
print('-depsc','-tiff','-r300','picture1')
```

saves the current figure at 300 dpi, in a color Encapsulated PostScript file named picture1.eps. The -tiff option creates a 72 dpi TIFF preview, which many word processor applications can display on screen after you import the EPS file. This enables you to view the picture on screen within your word processor and print the document to a PostScript printer using a resolution of 300 dpi.

See Also figure, hgsave, imwrite, orient, printdlg, printopt, saveas

Purpose	Print dialog box
Syntax	printdlg printdlg(fig) printdlg('-crossplatform',fig) printdlg('-setup',fig)
Description	printdlg prints the current figure.
	<pre>printdlg(fig) creates a modal dialog box from which you can print the figure window identified by the handle fig. Note that uimenus do not print.</pre>
	printdlg('-crossplatform',fig) displays the standard cross-platform MATLAB printing dialog rather than the built-in printing dialog box for Microsoft Windows computers. Insert this option before the fig argument.
	<pre>printdlg('-setup',fig) forces the printing dialog to appear in a setup mode. Here one can set the default printing options without actually printing.</pre>
	Note A modal dialog box prevents the user from interacting with other windows before responding. For more information, see WindowStyle in the MATLAB Figure Properties.
See Also	pagesetupdlg, printpreview

printpreview

Purpose	Preview figure to print
	Contents
	"GUI Alternative" on page 2-3094
	"Description" on page 2-3094
	"Right Pane Controls" on page 2-3095
	"The Layout Tab" on page 2-3096
	"The Lines/Text Tab" on page 2-3097
	"The Color Tab" on page 2-3099
	"The Advanced Tab" on page 2-3101
	"See Also" on page 2-3102
GUI Alternative	Use File > Print Preview on the figure window menu to access the Print Preview dialog box, described below. For details, see "Using Print Preview" in the MATLAB Graphics documentation.
Syntax	printpreview printpreview(f)
Description	printpreview displays a dialog box showing the figure in the currently active figure window as it will print. A scaled version of the figure displays in the right-hand pane of the GUI.
	printpreview(f) displays a dialog box showing the figure having the handle f as it will print.
	Use the Print Preview dialog box, shown below, to control the layout and appearance of figures before sending them to a printer or print file. Controls are grouped into four tabbed panes: Layout , Lines/Text , Color , and Advanced .

printpreview

🙏 Print Preview			_ 🗆 ×
StyleSheet default Save As	Zoom Over 💌	Print Refresh	Help Close
StyleSheet default Save As Layout Lines/Text Color Advanced Placement Auto (Actual Size, Centered) Use manual size and position Left: 0.25⁺ Top: 2.50⁺ Width: 8.00⁺ Height: 6.00⁺ Use defaults Fill page 			Help Close
Ose defaults Fini page Fix aspect ratio Center Paper Center Format: USLetter Width: 8.50 $\frac{1}{2}$ Height: 11.00 $\frac{1}{2}$ Units: Orientation © Inches © Portrait © Centimeters © Landscape © Points © Rotated		Pento dest of Normal distribution	

Right Pane Controls

You can position and scale plots on the printed page using the rulers in the right-hand pane of the Print Preview dialog. Use the outer ruler handlebars to change margins. Moving them changes plot proportions. Use the center ruler handlebars to change the position of the plot on the page. Plot proportions do not change, but you can move portions of the plot off the paper. The buttons on that pane let you refresh the plot, close the dialog (preserving all current settings), print the page immediately, or obtain context-sensitive help. Use the **Zoom** box and scroll bars to view and position page elements more precisely.

The Layout Tab

Use the **Layout** tab, shown above, to control the paper format and placement of the plot on printed pages. The following table summarizes the **Layout** options:

Group	Option	Description
Placement	Auto	Let MATLAB decide placement of plot on page
	Use manual	Specify position parameters for plot on page
	Top, Left, Width, Height	Standard position parameters in current units
	Use defaults	Revert to default position
	Fill page	Expand figure to fill printable area (see note below)
	Fix aspect ratio	Correct height/width ratio
	Center	Center plot on printed page
Paper	Format	U.S. and $\mathrm{ISO}^{\mathbb{R}}$ sheet size selector
	Width, Height	Sheet size in current units
Units	Inches	Use inches as units for dimensions and positions
	Centimeters	Use centimeters as units for dimensions and positions
	Points	Use points as units for dimensions and positions
Orientation	Portrait	Upright paper orientation

Group	Option	Description
	Landscape	Sideways paper orientation
	Rotated	Currently the same as Landscape

Note Selecting the **Fill page** option changes the PaperPosition property to fill the page, allowing objects in normalized units to expand to fill the space. If an object within the figure has an absolute size, for example a table, it can overflow the page when objects with normalized units expand. To avoid having objects fall off the page, do not use **Fill page** under such circumstances.

The Lines/Text Tab

Use the **Lines/Text** tab, shown below, to control the line weights, font characteristics, and headers for printed pages. The following table summarizes the **Lines/Text** options:

Layout Lines/Text Color Advanced			
Lines	- <u>Z</u>		
Line Width	💿 Default		
	◯ Scale By 0 %		
	C Custom 0.5 points		
Min Width	O Default		
	C Custom		
Text			
Font Name	O Default		
	O Custom Helvetica		
Font Size	Oefault		
	◯ Scale By 🛛		
	C Custom 10 roints		
Font Weigh	t Default		
Font Angle	Default		
Header			
Header Tex	t		
	Font		
Date Style	none		

Group	Option	Description
Lines	Line Width	Scale all lines by a percentage from 0 upward (100 being no change), print lines at a specified point size, or default line widths used on the plot
Min Width		Smallest line width (in points) to use when printing; defaults to 0.5 point
Text	Font Name	Select a system font for all text on plot, or default to fonts currently used on the plot

Group	Option	Description
	Font Size	Scale all text by a percentage from 0 upward (100 being no change), print text at a specified point size, or default to this
Weight text from drop-de		Select Normal Bold font styling for all text from drop-down menu or default to the font weights used on the plot
	Font Angle	Select Normal, Italic or Oblique font styling for all text from drop-down menu or default to the font angles used on the plot
Header	Header Header Type the text to appear on th Text the upper left of printed page blank for no header	
	Date Style	Select a date format to have today's date appear at the upper left of printed pages, or none for no date

The Color Tab

Use the **Color** tab, shown below, to control how colors are printed for lines and backgrounds. The following table summarizes the **Color** options:

Layout Lines/Text Cqr Advanced
Color Scale
C Black and White (Lines and Text only)
Gray Scale
Color
© RGB
С смук
Background color
C Same as figure

Group	Option	Description
Color Scale	Black and White	Select to print lines and text in black and white, but use color for patches and other objects
	Gray Scale	Convert colors to shades of gray on printed pages

Group	Option	Description
	Color	Print everything in color, matching colors on plot; select RGB (default) or CMYK color model for printing
Background Color	Same as figure	Print the figure's background color as it is
	Custom	Select a color name, or type a colorspec for the background; white (default) implies no background color, even on colored paper.

The Advanced Tab

Use the **Advanced** tab, shown below, to control finer details of printing, such as limits and ticks, renderer, resolution, and the printing of UIControls. The following table summarizes the **Advanced** options:

Layout Lines/Text Color Advanced			
Axes limits and ticks			
Recompute limits and ticks			
C Keep screen limits and ticks			
Miscellaneous			
Renderer auto			
Resolution auto			
Print UIControls			

Group	Option	Description
Axes limits and ticks	Recompute limits and ticks	Redraw <i>x</i> - and <i>y</i> -axes ticks and limits based on printed plot size (default)
	Keep limits and ticks	Use the <i>x</i> - and <i>y</i> -axes ticks and limits shown on the plot when printing the previewed figure
Miscellaneous	Renderer	Select a rendering algorithm for printing: painters, zbuffer, opengl, or auto (default)
	Resolution	Select resolution to print at in dots per inch: 150, 300, 600, or auto (default), or type in any other positive value
	Print UIControls	Print all visible UIControls in the figure (default), or uncheck to exclude them from being printed

See Also

printdlg, pagesetupdlg

For more information, see How to Print or Export in the MATLAB Graphics documentation.

Purpose	Product of array elements		
Syntax	<pre>B = prod(A) B = prod(A,dim)</pre>		
Description	B = prod(A) returns the products along different dimensions of an array.		
	If A is a vector, prod(A) returns the product of the elements.		
	If A is a matrix, prod(A) treats the columns of A as vectors, returning a row vector of the products of each column.		
	If A is a multidimensional array, prod(A) treats the values along the first non-singleton dimension as vectors, returning an array of row vectors.		
	B = prod(A,dim) takes the products along the dimension of A specified by scalar dim.		
Examples	The magic square of order 3 is		
	M = magic(3)		
	М =		
	8 1 6		
	3 5 7		
	4 9 2		
	The product of the elements in each column is		
	prod(M) =		
	96 45 84		
	The product of the elements in each row can be obtained by:		
	prod(M,2) =		
	48		

105 72

See Also

cumprod, diff, sum

Purpose	Profile execution time for function		
GUI Alternatives	As an alternative to the profile function, select Desktop > Profiler to open the Profiler.		
Syntax (1997)	<pre>profile on profile -history profile -nohistory profile -history -historysize integer profile -timer clock profile -history -historysize integer -timer clock profile off profile resume profile clear profile clear profile viewer S = profile(status') stats = profile('info')</pre>		
Description	The profile function helps you debug and optimize MATLAB code files by tracking their execution time. For each MATLAB function, MATLAB subfunction, or MEX-function in the file, profile records information about execution time, number of calls, parent functions, child functions, code line hit count, and code line execution time. Some people use profile simply to see the child functions; see also depfun for that purpose. To open the Profiler graphical user interface, use the profile viewer syntax. By default, Profiler time is CPU time. The total time reported by the Profiler is not the same as the time reported using the tic and toc functions or the time you would observe using a stopwatch.		

Note If your system uses Intel multi-core chips, you may want to restrict the active number of CPUs to 1 for the most accurate and efficient profiling. See "Intel Multi-Core Processors — Setting for Most Accurate Profiling on Windows Systems" or "Intel Multi-Core Processors — Setting for Most Accurate Profiling on Linux Systems" for details on how to do this.

profile on starts the Profiler, clearing previously recorded profile statistics. Note the following:

- You can specify all, none, or a subset, of the history, historysize and timer options with the profile on syntax.
- You can specify options in any order, including before or after on.
- If the Profiler is currently on and you specify profile with one of the options, MATLAB software returns an error message and the option has no effect. For example, if you specify profile timer real, MATLAB returns the following error: The profiler has already been started. TIMER cannot be changed.
- To change options, first specify profile off, and then specify profile on or profile resume with new options.

profile -history records the exact sequence of function calls. The profile function records, by default, up to 1,000,000 function entry and exit events. For more than 1,000,000 events, profile continues to record other profile statistics, but not the sequence of calls. To change the number of function entry and exit events that the profile function records, use the historysize option. By default, the history option is not enabled.

profile -nohistory disables further recording of the history (exact sequence of function calls). Use the -nohistory option after having previously set the -history option. All other profiling statistics continue to be collected.

profile **-history -historysize** *integer* specifies the number of function entry and exit events to record. By default, historysize is set to 1,000,000.

profile -timer clock specifies the type of time to use. Valid values
for clock are:

- 'cpu' The Profiler uses computer time (the default).
- 'real' The Profiler uses wall-clock time.

For example, cpu time for the pause function is typically small, but real time accounts for the actual time paused, and therefore would be larger.

profile -history -historysize integer -timer clock specifies all of the options. Any order is acceptable, as is a subset.

profile off stops the Profiler.

profile resume restarts the Profiler without clearing previously recorded statistics.

profile clear clears the statistics recorded by profile.

profile viewer stops the Profiler and displays the results in the Profiler window. For more information, see Profiling for Improving Performance in the Desktop Tools and Development Environment documentation.

S = profile(status') returns a structure containing information about the current status of the Profiler. The table lists the fields in the order that they appear in the structure.

Field	Values	Default Value
ProfilerStatus	'on' or 'off'	off
DetailLevel	'mmex'	'mmex'
Timer	'cpu' or 'real'	'cpu'

profile

Field	Values	Default Value
HistoryTrackin	g'on' or 'off'	'off'
HistorySize	integer	1000000

stats = profile('info') displays a structure containing the results.
Use this function to access the data generated by profile. The table
lists the fields in the order that they appear in the structure.

Field	Description
FunctionTable	Structure array containing statistics about each function called
FunctionHistory	Array containing function call history
ClockPrecision	Precision of the profile function's time measurement
ClockSpeed	Estimated clock speed of the CPU
Name	Name of the profiler

The FunctionTable field is an array of structures, where each structure contains information about one of the functions or subfunctions called during execution. The following table lists these fields in the order that they appear in the structure.

Field	Description
CompleteName	Full path to FunctionName, including subfunctions
FunctionName	Function name; includes subfunctions
FileName	Full path to FunctionName, with file extension, excluding subfunctions

Field	Description
Туре	MATLAB functions, MEX-functions, and many other types of functions including MATLABsubfunctions, nested functions, and anonymous functions
NumCalls	Number of times the function was called
TotalTime	Total time spent in the function and its child functions
TotalRecursiveTime	No longer used.
Children	FunctionTable indices to child functions
Parents	FunctionTable indices to parent functions
ExecutedLines	Array containing line-by-line details for the function being profiled.
	Column 1: Number of the line that executed. If a line was not executed, it does not appear in this matrix.
	Column 2: Number of times the line was executed
	Column 3: Total time spent on that line. Note: The sum of Column 3 entries does not necessarily add up to the function's TotalTime.
IsRecursive	BOOLEAN value: Logical 1 (true) if recursive, otherwise logical 0 (false)
PartialData	BOOLEAN value: Logical 1 (true) if function was modified during profiling, for example by being edited or cleared. In that event, data was collected only up until the point when the function was modified.

Examples Profile and Display Results

This example profiles the MATLAB magic command and then displays the results in the Profiler window. The example then retrieves the profile data on which the HTML display is based and uses the profsave command to save the profile data in HTML form.

```
profile on
plot(magic(35))
profile viewer
p = profile('info');
profsave(p,'profile results')
```

Profile and Save Results

Another way to save profile data is to store it in a MAT-file. This example stores the profile data in a MAT-file, clears the profile data from memory, and then loads the profile data from the MAT-file. This example also shows a way to bring the reloaded profile data into the Profiler graphical interface as live profile data, not as a static HTML page.

```
p = profile('info');
save myprofiledata p
clear p
load myprofiledata
profview(0,p)
```

Profile and Show Results Including History

This example illustrates an effective way to view the results of profiling when the history option is enabled. The history data describes the sequence of functions entered and exited during execution. The profile command returns history data in the FunctionHistory field of the structure it returns. The history data is a 2-by-n array. The first row contains Boolean values, where 0 means entrance into a function and 1 means exit from a function. The second row identifies the function being entered or exited by its index in the FunctionTable field. This example reads the history data and displays it in the MATLAB Command Window.

```
profile on -history
plot(magic(4));
p = profile('info');
for n = 1:size(p.FunctionHistory,2)
if p.FunctionHistory(1,n)==0
    str = 'entering function: ';
else
    str = 'exiting function: ';
end
disp([str p.FunctionTable(p.FunctionHistory(2,n)).FunctionName])
end
```

See Also depdir, depfun, mlint, profsave

Profiling for Improving Performance in the MATLAB Desktop Tools and Development Environment documentation


"Using the Parallel Profiler" in the Parallel Computing Toolbox documentation

profsave

Purpose	Save profile report in HTML format		
Syntax	profsave profsave(profinfo) profsave(profinfo,dirname)		
Description	profsave executes the profile('info') function and saves the results in HTML format. profsave creates a separate HTML file for each function listed in the FunctionTable field of the structure returned by profile. By default, profsave stores the HTML files in a subfolder of the current folder named profile_results.		
	profsave(profinfo) saves the profiling results, profinfo, in HTML format. profinfo is a structure of profiling information returned by the profile('info') function.		
	profsave(profinfo,dirname) saves the profiling results, profinfo, in HTML format. profsave creates a separate HTML file for each function listed in the FunctionTable field of profinfo and stores them in the folder specified by dirname.		
Examples	Run profile and save the results.		
	profile on plot(magic(5)) profile off profsave(profile('info'),'myprofile_results')		
See Also	profile		
	Profiling for Improving Performance in the MATLAB Desktop Tools and Development Environment documentation		

Purpose (

Open Property Editor



Syntax propedit propedit(handle_list)

Description propedit starts the Property Editor, a graphical user interface to the properties of graphics objects. If no current figure exists, propedit will create one.

propedit(handle_list) edits the properties for the object (or objects)
in handle_list.

Starting the Property Editor enables plot editing mode for the figure.

See Also inspect, plotedit, propertyeditor

propedit (COM)

Purpose	Open built-in property page for control
Syntax	h.propedit propedit(h)
Description	h.propedit requests the control to display its built-in property page. Note that some controls do not have a built-in property page. For those controls, this command fails.
	propedit(h) is an alternate syntax for the same operation.
Remarks	COM functions are available on Microsoft Windows systems only.
Examples	Create a Microsoft Calendar control and display its property page:
	cal = actxcontrol('mscal.calendar', [0 0 500 500]); cal.propedit
See Also	inspect, get (COM)

Purpose	Class property names
Syntax	<pre>properties('classname') properties(obj) p = properties()</pre>
Description	properties(' <i>classname</i> ') displays the names of the public properties for the MATLAB class named by classname. The properties function also displays inherited properties.
	<pre>properties(obj) obj can be either a scalar object or an array of objects. When obj is scalar, properties also returns dynamic properties. See "Dynamic Properties — Adding Properties to an Instance" for information on using dynamic properties.</pre>
	<pre>p = properties() returns the property names in a cell array of strings.</pre>
Definitions	A property is public when its GetAccess attribute value is public and its Hidden attribute value is false (default values for these attributes). See "Property Attributes" for a complete list of attributes.
	properties is also a MATLAB class-definition keyword. See classdef for more information on class definition keywords.
Examples	Retrieve the names of the public properties of class memmapfile and store the result in a cell array of strings:
	<pre>p = properties('memmapfile'); p ans =</pre>
	'writable' 'offset' 'format' 'repeat' 'filename'


Construct an instance of the ${\tt MException}$ class and get its properties names:

```
me = MException('Msg:ID','MsgText');
properties(me)
Properties for class MException:
```

identifier message cause stack

- **Alternatives** You can use the Workspace browser to browse current property values. See "MATLAB Workspace" for more information on using the Workspace browser.
- See Also fieldnames | events | methods
- **Tutorials** "Properties Storing Class Data"

Purpose Show or hide property editor



Purpose	Psi (polygamma) function
Syntax	Y = psi(X) Y = psi(k,X) Y = psi(k0:k1,X)
D · ··	

Description Y = psi(X) evaluates the ψ function for each element of array X. X must be real and nonnegative. The ψ function, also known as the digamma function, is the logarithmic derivative of the gamma function

$$\psi(x) = \operatorname{digamma}(x)$$
$$= \frac{d(\log(\Gamma(x)))}{dx}$$
$$= \frac{d(\Gamma(x)) / dx}{\Gamma(x)}$$

Y = psi(k,X) evaluates the kth derivative of ψ at the elements of X. psi(0,X) is the digamma function, psi(1,X) is the trigamma function, psi(2,X) is the tetragamma function, etc.

Y = psi(k0:k1,X) evaluates derivatives of order k0 through k1 at X. Y(k,j) is the (k-1+k0)th derivative of ψ , evaluated at X(j).

Examples Example 1

Use the psi function to calculate Euler's constant, y.

format long
-psi(1)
ans =
 0.57721566490153
-psi(0,1)
ans =
 0.57721566490153

Example 2

The trigamma function of 2, psi(1,2), is the same as $(\pi^2/6) - 1$.

```
format long
psi(1,2)
ans =
    0.64493406684823
pi^2/6 - 1
ans =
    0.64493406684823
```

Example 3

This code produces the first page of Table 6.1 in Abramowitz and Stegun [1].

```
x = (1:.005:1.250)';
[x gamma(x) gammaln(x) psi(0:1,x)' x-1]
```

Example 4

This code produces a portion of Table 6.2 in [1].

```
psi(2:3,1:.01:2)'
```

See Also gamma, gammainc, gammaln

References [1] Abramowitz, M. and I. A. Stegun, *Handbook of Mathematical Functions*, Dover Publications, 1965, Sections 6.3 and 6.4.

psi

publish

Purpose	Publish MATLAB file with code cells, saving output to specified file type		
Syntax	<pre>publish('file') publish('file','format') publish('file', options) my_doc = publish('file',)</pre>		
Description	<pre>publish('file') publishes file.m by running it in the base workspace, one cell at a time. It saves the code, comments, and results to an HTML output file, file.html. The MATLAB software stores this output file, along with other supporting output files, in a subfolder of the folder containing file.m. The subfolder is named html.</pre>		
	<pre>publish('file','format') saves the code, comments, and results to an output file, file.format. The output subfolder is named html, regardless of the output file format.</pre>		
	<pre>publish('file', options) publishes file.m using the structure options.</pre>		
	<pre>my_doc = publish('file',) returns the output resulting from publishing file.m to my_doc.</pre>		
Input	file		
Arguments	Specifies the file to publish.		
	format		
	Specifies the format to which you want to publish the file. Valid formats appear in the "Options for the publish Function" table under <i>options</i> .		
	options		
	A structure with the fields listed in the following table.		

Options for the publish Function

Field	Values
format	Specifies the output format for the published document: • 'doc' — Microsoft Word output format.
	• 'latex' — LaTeX output format.
	• 'ppt' — Microsoft PowerPoint output format.
	• 'xml' — Extensible Markup Language output format.
	• 'pdf' — Portable Document Format output format.
	If you specify 'pdf', then specify imageFormat as '.bmp' (the default) or '.jpg'.
	• 'html' (default)— Hypertext Markup Language output format.
	If you specify html, MATLAB includes the code at the end of the published HTML file as comments, even when you set the showCode option to false. Because MATLAB includes the code as comments, the code does not display in a Web browser. Use the grabcode function to extract the MATLAB code from the HTML file.
stylesheet	Specifies the Extensible Stylesheet Language (XSL) file that you want MATLAB to use when you specify a format of 'html', 'xml', or 'latex':
	• '' (default) — The MATLAB default stylesheet
	• XSL file name — The full path of the XSL file
outputDir	Specifies the folder to which you want MATLAB to publish the output document and its associated image files:
	• '' (default) — MATLAB places output in the html subfolder of the current folder, which MATLAB creates.
	• <i>full path</i> — MATLAB places output in the folder you specify.

Field	Values				
imageFormat	Specifies the file type for images that MATLAB produces when publishing files:			when	
	• 'png' (default unless format is latex or pdf)				
	• 'epsc2' (default when	format is i	latex)		
	• 'bmp' (default when fo	rmat is 'po	df')		
	Alternatively, '.jpg' when the format is 'pdf'				
	• Any format supported by print when figureSnapMethod is unless format is pdf			d is print,	
	 Any format supported b getframe, entireFigur format is pdf 	-	-	-	
figureSnapMethod	Specifies how figure windows and GUI dialog boxes that the code creates appear in published documents. <i>Window decorations</i> are the title bar, toolbar, menu bar, and window border.				
	Values	WindowBackgroundDecorations forColor for			
	values	 GUIs	Figures	GUIs	Figures
	'entireGUIWindow' (default)	Included	Excluded	Match screen	White
	'print'	Excluded	Excluded	White	White
	'getframe'	Excluded	Excluded	Match screen	Match screen
	'entireFigureWindow'	Included	Included	Match screen	Match screen

Field	Values
useNewFigure	A logical value that specifies whether MATLAB creates a Figure window for figures that the code generates:
	• true (default) — If the code generates a figure, then MATLAB creates a Figure window with a white background, and at the default size before publishing.
	• false — MATLAB does not create a figure window.
	This value enables you to use a figure with different properties for publishing. Open a Figure window, change the size and background color, for example, and then publish. Figures in your published document use the characteristics of the figure you opened before publishing.
maxHeight	 Specifies the maximum height, in pixels, for an image that the code generates: [] (default) — Height is unrestricted. Always used when the format is pdf.
	• Any positive integer — Height is the specified value.
maxWidth	 Specifies the maximum width, in pixels, for an image that the code generates: [] (default) — Width is unrestricted. Always used when the format is pdf.
	• Any positive integer — Width is the specified value.
showCode	Logical value that specifies whether MATLAB includes the code in the published document:
	• true (default)
	• false

Field	Values
evalCode	Logical value that specifies whether MATLAB runs the code that it is publishing: • true (default)
	Use this option if you want to run the code. If set to true and you are publishing a function file that requires inputs, specify the
	codeToEvaluate option too.
	• false
	Use this option if you do not want to run the code, but do want to present it (without output) in the published document. If you use the publish command to publish the file that contains the command, set this option to false. Otherwise, MATLAB attempts to publish the file recursively.
catchError	Logical value that specifies what MATLAB does if there is an error in the code that it is publishing:
	• true (default) — MATLAB continues publishing and includes the error in the published file.
	• false — MATLAB displays the error and publishing ends.
codeToEvaluate	Specifies the code that MATLAB is to evaluate. By default, MATLAB evaluates the code in the file you are publishing.

Field	Values
createThumbnail	Logical value that specifies whether MATLAB creates a thumbnail image of the published document:
	• true (default)
	• false
maxOutputLines	 Value that specifies the maximum number of output lines per cell that you want to publish before truncating the output: Inf (default) — MATLAB includes all output lines.
	• Nonnegative integer — MATLAB includes, at most, the number of lines you specify.
Examples	Copy sine_wave.m , publish the file to HTML, and then view the published document:
	copyfile(fullfile(docroot,'techdoc','matlab_env','examples', 'sine_wave.m'),'.','f')
	% When you run the command that follows, MATLAB runs sine_wave % and saves the code, comments, and results to % /html/sine_wave.html:
	<pre>publish('sine_wave.m', 'html')</pre>
	% View the published output file in the Web browser.

% View the published output file in the Web browser: web('html/sine_wave.html')

Copy sine_wave.m, publish the file to Microsoft Word format by using a structure, and then view the published document:

copyfile(fullfile(docroot,'techdoc','matlab_env','examples', ...

```
'sine_wave.m'),'.','f')
% Define the structure, options_doc_nocode,
% to exclude code from the output
% and publish to Microsoft Word format:
options_doc_nocode.format='doc'
options_doc_nocode.showCode=false
% Publish sine_wave.m:
publish('sine_wave.m',options_doc_nocode)
% View the published output file in Microsoft Word:
winopen('html/sine_wave.doc')
Copy collatz.m, create a structure to specify the input values, publish
the file to HTML, and then view the published document:
copyfile(fullfile(docroot,'techdoc','matlab_env','examples', ...
```

```
% Create a structure, opts, that contains the code that you
% want collatz.m to evaluate when it runs:
opts.codeToEvaluate = 'n = 3; collatz(n)';
```

```
% In the MATLAB Web browser, display the results of
% publishing collatz.m when it runs with the values
% specified in opts:
web(publish('collatz',opts))
```

'collatz.m'), '.', 'f')

Copy sine_wave.m, publish the file capturing window decorations, and then view the published document:

```
copyfile(fullfile(docroot,'techdoc','matlab_env','examples', ...
'sine_wave.m'),'.','f')
```

% Create an options file that causes the published document % to capture window decorations:

	function_options.format='html'; function_options.figureSnapMethod='entireGUIWindow';
	<pre>% Publish the script using the options file: publish('sine_wave.m',function_options);</pre>
	% View the output in the MATLAB Web browser web('html/sine_wave.html')
	Publish a demo file to PDF, and then open the published document:
	open(publish('sparsity',struct('format','pdf','outputDir',tempname)
Alternatives	To publish a file from the desktop:
	1 Open the MATLAB code file that you want to publish in the Editor.
	2 Choose one of the following:
	 Publish with default options by choosing File > Publish filename.
	 Publish with customized options by choosing File > Publish Configuration for filename > Edit Publish Configurations for filename, and then adjust the Publish settings.
See Also	grabcode notebook
How To	"Publishing MATLAB Code Files"
	"Defining Code Cells"

Purpose	Store character array in Automation server
Syntax	MATLAB Client h.PutCharArray('varname', ' <i>workspace</i> ', 'string') PutCharArray(h, 'varname', ' <i>workspace</i> ', 'string') invoke(h, ' PutCharArray ', 'varname', ' <i>workspace</i> ', 'string')
	IDL Method Signature PutCharArray([in] BSTR varname, [in] BSTR workspace, [in] BSTR string)
	Microsoft Visual Basic Client PutCharArray(varname As String, workspace As String, string As String)
Description	PutCharArray stores the character array in string in the specified workspace of the server attached to handle h, assigning to it the variable varname. The workspace argument can be either base or global.
Remarks	The character array specified in the string argument can have any dimensions. However, PutCharArray changes the dimensions to a 1-by-n column-wise representation, where n is the number of characters in the array. Executing the following commands in MATLAB illustrates this behavior:
	<pre>h = actxserver('matlab.application'); chArr = ['abc'; 'def'; 'ghk'] chArr = abc def ghk</pre>
	h.PutCharArray('Foo', 'base', chArr) tstArr = h.GetCharArray('Foo', 'base') tstArr = adgbehcfk

Server function names, like PutCharArray, are case sensitive when using the dot notation syntax shown in the Syntax section.

There is no difference in the operation of the three syntaxes shown above for the MATLAB client.

Examples Store string str in the base workspace of the server using PutCharArray.

MATLAB Client

```
h = actxserver('matlab.application');
h.PutCharArray('str', 'base', ...
    'He jests at scars that never felt a wound.')
S = h.GetCharArray('str', 'base')
S =
    He jests at scars that never felt a wound.
```

Visual Basic .NET Client

This example uses the Visual Basic MsgBox command to control flow between MATLAB and the Visual Basic Client.

```
Dim Matlab As Object
Try
    Matlab = GetObject(, "matlab.application")
Catch e As Exception
    Matlab = CreateObject("matlab.application")
End Try
MsgBox("MATLAB window created; now open it...")
```

Open the MATLAB window, then click Ok.

```
Matlab.PutCharArray("str", "base", ______
"He jests at scars that never felt a wound.")
MsgBox("In MATLAB, type" & vbCrLf ______
& "str")
```

```
In the MATLAB window type str; MATLAB displays:

str =

He jests at scars that never felt a wound.

Click Ok.

MsgBox("closing MATLAB window...")

Click Ok to close and terminate MATLAB.

Matlab.Quit()

See Also

GetCharArray, PutWorkspaceData, GetWorkspaceData, Execute
```

Purpose Matrix in Automation server workspace

Syntax MATLAB Client

h.PutFullMatrix('varname', 'workspace', xreal, ximag)
PutFullMatrix(h, 'varname', 'workspace', xreal, ximag)

IDL Method Signature

PutFullMatrix([in] BSTR varname, [in] BSTR workspace, [in] SAFEARRAY(double) xreal, [in] SAFEARRAY(double) ximag)

Microsoft Visual Basic Client

PutFullMatrix([in] varname As String, [in] workspace As String, [in] xreal As Double, [in] ximag As Double)

Description h.PutFullMatrix('varname', 'workspace', xreal, ximag) stores a matrix in the specified workspace of the server attached to handle h and assigns it to variable varname. Use xreal and ximag for the real and imaginary parts of the matrix. The matrix cannot be a scalar, an empty array, or have more than two dimensions. The values for workspace are base or global.

> PutFullMatrix(h, 'varname', 'workspace', xreal, ximag) is an alternate syntax.

For VBScript clients, use the GetWorkspaceData and PutWorkspaceData functions to pass numeric data to and from the MATLAB workspace. These functions use the variant data type instead of safearray which is not supported by VBScript.

Examples Use a MATLAB client to write a matrix to the base workspace of the server:

```
h = actxserver('matlab.application');
h.PutFullMatrix('M', 'base', rand(5), zeros(5))
%Use one output for real values only
xreal = h.GetFullMatrix('M', 'base', zeros(5), zeros(5))
```

Use a Visual Basic .NET client to write a matrix to the base workspace of the server:

```
Dim MatLab As Object
Dim XReal(4, 4) As Double
Dim XImag(4, 4) As Double
Dim ZReal(4, 4) As Double
Dim ZImag(4, 4) As Double
Dim i, j As Integer
For i = 0 To 4
For j = 0 To 4
XReal(i, j) = Rnd() * 6
XImag(i, j) = 0
Next j
Next i
MatLab = CreateObject("matLab.application")
MatLab.PutFullMatrix("M", "base", XReal, XImag)
MatLab.GetFullMatrix("M", "base", ZReal, ZImag)
```

Use a MATLAB client to write a matrix to the global workspace of the server:

```
h = actxserver('matlab.application');
h.PutFullMatrix('X', 'global', [1 3 5; 2 4 6], ...
    [1 1 1; 1 1 1])
h.invoke('Execute', 'whos global')
```

Use a Visual Basic .NET client to write a matrix to the global workspace of the server:

```
Dim MatLab As Object
Dim XReal(1, 2) As Double
Dim XImag(1, 2) As Double
Dim result As String
Dim i, j As Integer
For i = 0 To 1
For j = 0 To 2
XReal(i, j) = (j * 2 + 1) + i
XImag(i, j) = 1
Next j
Next i
Matlab = CreateObject("matlab.application")
MatLab.PutFullMatrix("X", "global", XReal, XImag)
result = Matlab.Execute("whos global")
MsgBox(result)
```

PutFullM	•	×
Name	Size	Bytes Class
х	2x3	96 double array (global complex)
Grand to	otal is 6	elements using 96 bytes
		ОК

See Also GetFullMatrix | PutWorkspaceData | Execute

- **How To** "MATLAB COM Automation Server Support"
 - "Exchanging Data with the Server"

Purpose

Syntax	MATLAB Client h.PutWorkspaceData('varname', ' <i>workspace</i> ', data) PutWorkspaceData(h, 'varname', ' <i>workspace</i> ', data)				
	IDL Method Signature				
	PutWorkspaceData([in] BSTR varname, [in] BSTR workspace, [in] VARIANT data)				
	Microsoft Visual Basic Client				
	PutWorkspaceData(varname As String, workspace As String, data As Object)				
Description	h.PutWorkspaceData('varname', ' <i>workspace</i> ', data) stores data in the workspace of the server attached to handle h and assigns it to varname. The values for <i>workspace</i> are base or global.				
	PutWorkspaceData(h, 'varname', ' <i>workspace</i> ', data) is an alternate syntax.				
	Use PutWorkspaceData to pass numeric and character array data respectively to the server. Do <i>not</i> use PutWorkspaceData on sparse arrays, structures, or function handles. Use the Execute method for these data types.				
	The GetWorkspaceData and PutWorkspaceData functions pass numeric data as a variant data type. These functions are especially useful for VBScript clients as VBScript does not support the safearray data type used by GetFullMatrix and PutFullMatrix.				
Examples	Create an array in a MATLAB client and put it in the base workspace of the MATLAB Automation server:				
	<pre>h = actxserver('matlab.application'); for i = 0:6 data(i+1) = i * 15; end</pre>				

Data in Automation server workspace

h.PutWorkspaceData('A', 'base', data)

Create an array in a Visual Basic client and put it in the base workspace of the MATLAB Automation server:

1 Create the Visual Basic application. Use the MsgBox command to control flow between MATLAB and the application:

```
Dim Matlab As Object
Dim data(6) As Double
Dim i As Integer
MatLab = CreateObject("matlab.application")
For i = 0 To 6
    data(i) = i * 15
Next i
MatLab.PutWorkspaceData("A", "base", data)
MsgBox("In MATLAB, type" & vbCrLf & "A")
```

2 Open the MATLAB window and type A. MATLAB displays:

A = 0 15 30 45 60 75 90

- **3** Click **Ok** to close and terminate MATLAB.
- See Also GetWorkspaceData | PutFullMatrix | PutCharArray | Execute
- **How To** "Executing Commands in the MATLAB Server"
 - "Exchanging Data with the Server"

pwd

Purpose	Identify current folder
Syntax	pwd currentFolder = pwd
Description	<pre>pwd displays the MATLAB current folder. currentFolder = pwd returns the current folder as a string to currentFolder.</pre>
Alternatives	Use the Current Folder field in the MATLAB desktop toolbar.Use address bar in the Current Folder browser.
See Also	cd dir
How To	• "Tools for Managing Files"

Purpose	Quasi-minimal residual method
Syntax	<pre>x = qmr(A,b) qmr(A,b,tol) qmr(A,b,tol,maxit) qmr(A,b,tol,maxit,M) qmr(A,b,tol,maxit,M1,M2) qmr(A,b,tol,maxit,M1,M2,x0) [x,flag] = qmr(A,b,) [x,flag,relres] = qmr(A,b,) [x,flag,relres,iter] = qmr(A,b,) [x,flag,relres,iter,resvec] = qmr(A,b,)</pre>
Description	x = qmr(A,b) attempts to solve the system of linear equations A*x=b for x. The n-by-n coefficient matrix A must be square and should be large and sparse. The column vector b must have length n. A can be a function handle afun such that afun(x, 'notransp') returns A*x and afun(x, 'transp') returns A'*x. See "Function Handles" in the MATLAB Programming documentation for more information. "Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide additional parameters to the function afun, as well as the preconditioner function mfun described
	below, if necessary. If qmr converges, a message to that effect is displayed. If qmr fails to converge after the maximum number of iterations or halts for any reason, a warning message is printed displaying the relative residual norm(b-A*x)/norm(b) and the iteration number at which the method stopped or failed.
	<pre>qmr(A,b,tol) specifies the tolerance of the method. If tol is [], then qmr uses the default, 1e-6.</pre>
	<pre>qmr(A,b,tol,maxit) specifies the maximum number of iterations. If maxit is [], then qmr uses the default, min(n,20).</pre>
	qmr(A,b,tol,maxit,M) and $qmr(A,b,tol,maxit,M1,M2)$ use preconditioners M or M = M1*M2 and effectively solve the system

inv(M)*A*x = inv(M)*b for x. If M is [] then qmr applies no preconditioner. M can be a function handle mfun such that mfun(x, 'notransp') returns M\x and mfun(x, 'transp') returns M'\x.

qmr(A,b,tol,maxit,M1,M2,x0) specifies the initial guess. If x0 is [], then qmr uses the default, an all zero vector.

[x,flag] = qmr(A,b,...) also returns a convergence flag.

Flag	Convergence
0	qmr converged to the desired tolerance tol within maxit iterations.
1	qmr iterated maxit times but did not converge.
2	Preconditioner M was ill-conditioned.
3	The method stagnated. (Two consecutive iterates were the same.)
4	One of the scalar quantities calculated during qmr became too small or too large to continue computing.

Whenever flag is not 0, the solution x returned is that with minimal norm residual computed over all the iterations. No messages are displayed if the flag output is specified.

[x,flag,relres] = qmr(A,b,...) also returns the relative residual norm(b-A*x)/norm(b). If flag is 0, relres <= tol.</pre>

[x,flag,relres,iter] = qmr(A,b,...) also returns the iteration
number at which x was computed, where 0 <= iter <= maxit.</pre>

[x,flag,relres,iter,resvec] = qmr(A,b,...) also returns a vector of the residual norms at each iteration, including norm(b-A*x0).

Examples Example 1

n = 100; on = ones(n,1);

```
A = spdiags([-2*on 4*on -on],-1:1,n,n);
b = sum(A,2);
tol = 1e-8; maxit = 15;
M1 = spdiags([on/(-2) on],-1:0,n,n);
M2 = spdiags([4*on -on],0:1,n,n);
x = qmr(A,b,tol,maxit,M1,M2);
```

displays the message

```
qmr converged at iteration 9 to a solution...
with relative residual
5.6e-009
```

Example 2

This example replaces the matrix A in Example 1 with a handle to a matrix-vector product function afun. The example is contained in an M-file run_qmr that

- Calls qmr with the function handle @afun as its first argument.
- Contains afun as a nested function, so that all variables in run_qmr are available to afun.

The following shows the code for run_qmr:

```
function x1 = run_qmr
n = 100;
on = ones(n,1);
A = spdiags([-2*on 4*on -on],-1:1,n,n);
b = sum(A,2);
tol = 1e-8;
maxit = 15;
M1 = spdiags([on/(-2) on],-1:0,n,n);
M2 = spdiags([4*on -on],0:1,n,n);
x1 = qmr(@afun,b,tol,maxit,M1,M2);
function y = afun(x,transp_flag)
if strcmp(transp_flag,'transp') % y = A'*x
```

```
y = 4 * x;

y(1:n-1) = y(1:n-1) - 2 * x(2:n);

y(2:n) = y(2:n) - x(1:n-1);

elseif strcmp(transp_flag, 'notransp') % y = A*x

y = 4 * x;

y(2:n) = y(2:n) - 2 * x(1:n-1);

y(1:n-1) = y(1:n-1) - x(2:n);

end

end
```

When you enter

end

```
x1=run_qmr;
```

MATLAB software displays the message

```
qmr converged at iteration 9 to a solution with relative residual 5.6e{-}009
```

Example 3

load west0479; A = west0479; b = sum(A,2); [x,flag] = qmr(A,b)


flag is 1 because qmr does not converge to the default tolerance 1e-6 within the default 20 iterations.

```
[L1,U1] = luinc(A,1e-5);
[x1,flag1] = qmr(A,b,1e-6,20,L1,U1)
```

flag1 is 2 because the upper triangular U1 has a zero on its diagonal, and qmr fails in the first iteration when it tries to solve a system such as U1*y = r for y using backslash.

```
[L2,U2] = luinc(A,1e-6);
[x2,flag2,relres2,iter2,resvec2] = qmr(A,b,1e-15,10,L2,U2)
```

flag2 is 0 because qmr converges to the tolerance of 1.6571e-016 (the value of relres2) at the eighth iteration (the value of iter2) when preconditioned by the incomplete LU factorization with a drop tolerance of 1e-6. resvec2(1) = norm(b) and resvec2(9) = norm(b-A*x2). You can follow the progress of qmr by plotting the relative residuals at each iteration starting from the initial estimate (iterate number 0).



See Also bicg, bicgstab, cgs, gmres, lsqr, luinc, minres, pcg, symmlq, function_handle (@), mldivide (\)

References [1] Barrett, R., M. Berry, T. F. Chan, et al., *Templates for the Solution of Linear Systems: Building Blocks for Iterative Methods*, SIAM, Philadelphia, 1994.

[2] Freund, Roland W. and Nöel M. Nachtigal, "QMR: A quasi-minimal residual method for non-Hermitian linear systems," *SIAM Journal: Numer. Math.* 60, 1991, pp. 315-339.

Purpose	Orthogonal-triangular decomposition				
Syntax (1997)	[Q,R] = qr(A) [Q,R] = qr(A,0) [Q,R,E] = qr(A) [Q,R,E] = qr(A,0) X = qr(A) X = qr(A,0) R = qr(A,0) [C,R] = qr(A,B) [C,R,E] = qr(A,B,0) [C,R,E] = qr(A,B,0) [C,R,E] = qr(A,B,0)				
Description	[Q,R] = qr(A), where A is m-by-n, produces an m-by-n upper triangular matrix R and an m-by-m unitary matrix Q so that A = Q*R.				
	[Q,R] = qr(A,0) produces the economy-size decomposition. If $m > n$, only the first n columns of Q and the first n rows of R are computed. If $m <= n$, this is the same as $[Q,R] = qr(A)$.				
	If A is full:				
	[Q,R,E] = qr(A) produces unitary Q, upper triangular R and a permutation matrix E so that A*E = Q*R. The column permutation E is chosen so that abs(diag(R)) is decreasing.				
	[Q,R,E] = qr(A,0) produces an economy-size decomposition in which E is a permutation vector, so that $A(:,E) = Q*R$.				
	X = qr(A) and $X = qr(A,0)$ return a matrix X such that triu(X) is the upper triangular factor R.				
	If A is sparse:				
	R = qr(A) computes a Q-less QR decomposition and returns the upper triangular factor R. Note that $R = CHOL(A'*A)$. Since Q is often nearly full, this is preferred to $[Q,R] = QR(A)$.				
	R = qr(A,0) produces economy-size R. If m>n, R has only n rows. If m<=n, this is the same as $R = qr(A)$.				

qr

	[Q,R,E] = qr(A) produces unitary Q, upper triangular R and a
	permutation matrix E so that A*E = Q*R. The column permutation E is chosen to reduce fill-in in R.
	[Q,R,E] = qr(A,0) produces an economy-size decomposition in which E is a permutation vector, so that A(:,E) = Q*R.
	[C,R] = qr(A,B), where B has as many rows as A, returns C = Q'*B. The least-squares solution to A*X = B is X = R\C.
	$[C,R,E] = qr(A,B)$, also returns a fill-reducing ordering. The least-squares solution to $A*X = B$ is $X = E*(R\setminus C)$.
	[C,R] = qr(A,B,0) produces economy-size results. If m>n, C and R have only n rows. If m<=n, this is the same as $[C,R] = qr(A,B)$.
	[C,R,E] = qr(A,B,0) additionally produces a fill-reducing permutation vector E. In this case, the least-squares solution to A*X = B is X(E,:) = R\C.
Examples	Find the least squares approximate solution to $A*x = b$ with the Q-less QR decomposition and one step of iterative refinement:
	<pre>if issparse(A), R = qr(A); else R = triu(qr(A)); end x = R\(R'\(A'*b)); r = b - A*x; e = R\(R'\(A'*r)); x = x + e;</pre>
See Also	lu ldl

Purpose	Remove column or row from QR factorization				
Syntax	<pre>[Q1,R1] = qrdelete(Q,R,j) [Q1,R1] = qrdelete(Q,R,j,'col') [Q1,R1] = qrdelete(Q,R,j,'row')</pre>				
Description	[Q1,R1] = qrdelete(Q,R,j) returns the QR factorization of the matrix A1, where A1 is A with the column A(:,j) removed and $[Q,R] = qr(A)$ is the QR factorization of A.				
	[Q1,R1] = qrdelete(Q,R,j,'col') is the same as qrdelete(Q,R,j).				
	[Q1,R1] = qrdelete(Q,R,j,'row') returns the QR factorization of the matrix A1, where A1 is A with the row A(j,:) removed and $[Q,R] = qr(A)$ is the QR factorization of A.				
Examples	A = magic(5); [Q,R] = qr(A); j = 3; [Q1,R1] = qrdelete(Q,R,j,'row');				
	Q1 =				
	0.5274 -0.5197 -0.6697 -0.0578				
	0.7135 0.6911 0.0158 0.1142				
	0.3102 -0.1982 0.4675 -0.8037				
	0.3413 -0.4616 0.5768 0.5811				
	R1 =				
	32.2335 26.0908 19.9482 21.4063 23.3297				
	0 -19.7045 -10.9891 0.4318 -1.4873				
	0 0 22.7444 5.8357 -3.1977				
	0 0 0 -14.5784 3.7796				

returns a valid $\ensuremath{\mathsf{QR}}\xspace$ factorization, although possibly different from

A2 = A; A2(j,:) = []; [Q2,R2] = qr(A2)

	Q2 =					
	-0.5274	0.5197	0.6697	-0.0578		
	-0.7135	-0.6911	-0.0158	0.1142		
	-0.3102	0.1982	-0.4675	-0.8037		
	-0.3413	0.4616	-0.5768	0.5811		
	R2 =					
	-32.2335	-26.0908	-19.9482	-21.4063	-23.3297	
	0	19.7045	10.9891	-0.4318	1.4873	
	0	0	-22.7444	-5.8357	3.1977	
	0	0	0	-14.5784	3.7796	
Algorithm	The qrdelete fu appropriate eler				ions to zero o	ut the

See Also planerot, qr, qrinsert

Purpose	Insert column or row into QR factorization					
Syntax	[Q1,R1] = qrinsert(Q,R,j,x) [Q1,R1] = qrinsert(Q,R,j,x,'col') [Q1,R1] = qrinsert(Q,R,j,x,'row')					
Description	<pre>[Q1,R1] = qrinsert(Q,R,j,x) returns the QR factorization of the matrix A1, where A1 is A = Q*R with the column x inserted before A(:,j). If A has n columns and j = n+1, then x is inserted after the last column of A. [Q1,R1] = qrinsert(Q,R,j,x,'col') is the same as</pre>					
	qrinsert(Q,R,j		,x, coi) .	is the same	as	
	[Q1,R1] = qrin of the matrix A1, before A(j,:).					
Examples	<pre>A = magic(5); [Q,R] = qr(A); j = 3; x = 1:5; [Q1,R1] = qrinsert(Q,R,j,x,'row')</pre>					
	Q1 = 0.5231 0.7078 0.0308 0.1231 0.3077 0.3385	0.5039 -0.6966 0.0592 0.1363 0.1902 0.4500	-0.6750 0.0190 0.0656 0.3542 0.4100 0.4961	0.1205 -0.0788 0.1169 0.6222 0.4161 -0.6366	0.0411 0.0833 0.1527 0.6398 -0.7264 0.1761	0.0225 -0.0150 -0.9769 0.2104 -0.0150 0.0225
	R1 = 32.4962 0 0 0	26.6801 19.9292 0 0	21.4795 12.4403 24.4514 0	23.8182 2.1340 11.8132 20.2382	26.0031 4.3271 3.9931 10.3392	

qrinsert

0	0	0	0	16.1948
0	0	0	0	0

returns a valid QR factorization, although possibly different from

```
A2 = [A(1:j-1,:); x; A(j:end,:)];
[Q2,R2] = qr(A2)
```

Q2 =					
-0.5231	0.5039	0.6750	-0.1205	0.0411	0.0225
-0.7078	-0.6966	-0.0190	0.0788	0.0833	-0.0150
-0.0308	0.0592	-0.0656	-0.1169	0.1527	-0.9769
-0.1231	0.1363	-0.3542	-0.6222	0.6398	0.2104
-0.3077	0.1902	-0.4100	-0.4161	-0.7264	-0.0150
-0.3385	0.4500	-0.4961	0.6366	0.1761	0.0225
R2 =					
-32.4962	-26.6801	-21.4795	-23.8182	-26.0031	
0	19.9292	12.4403	2.1340	4.3271	
0	0	-24.4514	-11.8132	-3.9931	
0	0	0	-20.2382	-10.3392	
0	0	0	0	16.1948	
0	0	0	0	0	

- **Algorithm** The qrinsert function inserts the values of x into the jth column (row) of R. It then uses a series of Givens rotations to zero out the nonzero elements of R on and below the diagonal in the jth column (row).
- **See Also** planerot, qr, qrdelete

Description	Rank 1 update to QR factorization
Syntax	[Q1,R1] = qrupdate(Q,R,u,v)
Description	[Q1,R1] = qrupdate(Q,R,u,v) when $[Q,R] = qr(A)$ is the original QR factorization of A, returns the QR factorization of A + u*v', where u and v are column vectors of appropriate lengths.
Remarks	qrupdate works only for full matrices.
Examples	The matrix
	mu = sqrt(eps)
	mu =
	1.4901e-08
	A = [ones(1,4); mu*eye(4)];
	is a well-known example in least squares that indicates the dangers of forming A'*A. Instead, we work with the QR factorization – orthonormal Q and upper triangular R.
	[Q,R] = qr(A);
	As we expect, R is upper triangular.
	R =

-1.0000	-1.0000	-1.0000	-1.0000
0	0.0000	0.0000	0.0000
0	0	0.0000	0.0000
0	0	0	0.0000
0	0	0	0

qrupdate

In this case, the upper triangular entries of R, excluding the first row, are on the order of sqrt(eps).

Consider the update vectors

 $u = [-1 \ 0 \ 0 \ 0]'; v = ones(4,1);$

Instead of computing the rather trivial QR factorization of this rank one update to A from scratch with

[QT,RT] = qr(A + u*v')QT = 0 1 0 0 0 - 1 0 0 0 0 0 -1 0 0 0 0 0 - 1 0 0 0 0 0 - 1 0 RT = 1.0e-007 * -0.1490 0 0 0 -0.1490 0 0 0 0 0 -0.1490 0 0 0 -0.14900 0 0 0 0 we may use grupdate. [Q1,R1] = qrupdate(Q,R,u,v)Q1 = -0.0000 -0.0000 -0.0000 -0.0000

	0.0000	1.0000	-0.0000	-0.0000	0.0000
	0.0000	0.0000	1.0000	-0.0000	0.0000
	-0.0000	-0.0000	-0.0000	1.0000	0.0000
	R1 =				
	1.0e-007	*			
	0.1490	0.0000	0.0000	0.0000	
	0	0.1490	0.0000	0.0000	
	0	0	0.1490	0.0000	
	0	0	0	0.1490	
	0	0	0	0	
	Note that both fa	actorizations	are correct,	even though	they are different.
Algorithm	if we take $N = r$	<i>tions</i> by Gol nax(m,n), th oughly an O	ub and van 1 Ien computin (N ³) algori	Loan. qrupdang the new G thm, while si	ate is useful since,
References	[1] Golub, Gene Edition, Johns H			-	omputations, Third 1996
See Also	cholupdate, qr				

Purpose Numerically evaluate integral, adaptive Simpson quadrature

Syntax q = quad(fun,a,b) q = quad(fun,a,b,tol) q = quad(fun,a,b,tol,trace) [q,fcnt] = quad(...)

Description *Quadrature* is a numerical method used to find the area under the graph of a function, that is, to compute a definite integral.

$$q = \int_{a}^{b} f(x) dx$$

q = quad(fun,a,b) tries to approximate the integral of function fun from a to b to within an error of 1e-6 using recursive adaptive Simpson quadrature. fun is a function handle. See "Function Handles" in the MATLAB Programming documentation for more information. Limits a and b must be finite. The function y = fun(x) should accept a vector argument x and return a vector result y, the integrand evaluated at each element of x.

"Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide additional parameters to the function fun, if necessary.

q = quad(fun,a,b,tol) uses an absolute error tolerance tol instead of the default which is 1.0e-6. Larger values of tol result in fewer function evaluations and faster computation, but less accurate results. In MATLAB version 5.3 and earlier, the quad function used a less reliable algorithm and a default relative tolerance of 1.0e-3.

q = quad(fun,a,b,tol,trace) with non-zero trace shows the values
of [fcnt a b-a Q] during the recursion.

[q,fcnt] = quad(...) returns the number of function evaluations.

The function quad1 may be more efficient with high accuracies and smooth integrands.

The list below contains information to help you determine which quadrature function in MATLAB to use:

- The quad function may be most efficient for low accuracies with nonsmooth integrands.
- The quad1 function may be more efficient than quad at higher accuracies with smooth integrands.
- The quadgk function may be most efficient for high accuracies and oscillatory integrands. It supports infinite intervals and can handle moderate singularities at the endpoints. It also supports contour integration along piecewise linear paths.
- The quadv function vectorizes quad for an array-valued fun.
- If the interval is infinite, [a, Inf), then for the integral of fun(x) to exist, fun(x) must decay as x approaches infinity, and quadgk requires it to decay rapidly. Special methods should be used for oscillatory functions on infinite intervals, but quadgk can be used if fun(x) decays fast enough.
- The quadgk function will integrate functions that are singular at finite endpoints if the singularities are not too strong. For example, it will integrate functions that behave at an endpoint c like log|x-c| or |x-c|^p for p >= -1/2. If the function is singular at points inside (a,b), write the integral as a sum of integrals over subintervals with the singular points as endpoints, compute them with quadgk, and add the results.

Example

To compute the integral

$$\int_{0}^{2} \frac{1}{x^{3} - 2x - 5} dx$$

write an M-file function myfun that computes the integrand:

function y = myfun(x)
y = 1./(x.^3-2*x-5);

Then pass @myfun, a function handle to myfun, to quad, along with the limits of integration, 0 to 2: Q = quad(@myfun, 0, 2)Q = -0.4605Alternatively, you can pass the integrand to quad as an anonymous function handle F: $F = @(x)1./(x.^{3}-2*x-5);$ Q = quad(F, 0, 2);Algorithm quad implements a low order method using an adaptive recursive Simpson's rule. **Diagnostics** quad may issue one of the following warnings: 'Minimum step size reached' indicates that the recursive interval subdivision has produced a subinterval whose length is on the order of roundoff error in the length of the original interval. A nonintegrable singularity is possible. 'Maximum function count exceeded' indicates that the integrand has been evaluated more than 10,000 times. A nonintegrable singularity is likely. 'Infinite or Not-a-Number function value encountered' indicates a floating point overflow or division by zero during the evaluation of the integrand in the interior of the interval. See Also quad2d, dblquad, quadgk, quadl, quadv, trapz, triplequad, function handle (@), "Anonymous Functions" References [1] Gander, W. and W. Gautschi, "Adaptive Quadrature – Revisited," BIT, Vol. 40, 2000, pp. 84-101. This document is also available at http://www.inf.ethz.ch/personal/gander.

Purpose	Numerically evaluate dou	ble integral over planar region
Syntax	q = quad2d(fun,a,b,c, [q,errbnd] = quad2d(. q = quad2d(fun,a,b,c,	
Description	 q = quad2d(fun,a,b,c,d) approximates the integral of fun(x,y) over the planar region a ≤ x ≤ b and c(x) ≤ y ≤ d(x). fun is a function handle, c and d may each be a scalar or a function handle. All input functions must be vectorized. The function Z=fun(X,Y) must accept 2-D matrices X and Y of the same size and return a matrix Z of corresponding values. The functions ymin=c(X) and ymax=d(X) must accept matrices and return matrices of the same size with corresponding values. [q,errbnd] = quad2d(). errbnd is an approximate upper bound on the absolute error, Q - I , where I denotes the exact value of the integral. q = quad2d(fun,a,b,c,d,param1,val1,param2,val2,) performs the integration as above with specified values of optional parameters: 	
	RelTol	relative error tolerance
	quad2d attempts to satisfy ERRBND <= max(AbsTol,RelTol* Q). This	

The MaxFunEvals parameter limits the number of vectorized calls to fun. The default is 2000.

FailurePlot	Generate a plot if MaxFunEvals is reached.
-------------	--

Setting FailurePlot to true generates a graphical representation of the regions needing further refinement when MaxFunEvals is reached. No plot is generated if the integration succeeds before reaching MaxFunEvals. These (generally) 4-sided regions are mapped to rectangles internally. Clusters of small regions indicate the areas of difficulty. The default is false.

Singular Problem may have boundary singularities
--

With Singular set to true, quad2d will employ transformations to weaken boundary singularities for better performance. The default is true. Setting Singular to false will turn these transformations off, which may provide a performance benefit on some smooth problems.

Examples Example 1

Integrate $y\sin(x) + x\cos(y)$ over $\pi \le x \le 2\pi$, $0 \le y \le \pi$. The true value of the integral is $-\pi^2$.

```
Q = quad2d(@(x,y) y.*sin(x)+x.*cos(y),pi,2*pi,0,pi)
```

Example 2

Integrate $[(x+y)^{1/2}(1+x+y)^2]^{-1}$ over the triangle $0 \le x \le 1$ and $0 \le y \le 1-x$. The integrand is infinite at (0,0). The true value of the integral is $\pi/4 - 1/2$.

fun = $@(x,y) \ 1./(sqrt(x + y) \ .* \ (1 + x + y) \ .^2)$

In Cartesian coordinates:

ymax = @(x) 1 - x;

Q = quad2d(fun, 0, 1, 0, ymax)

In polar coordinates:

```
polarfun = @(theta,r) fun(r.*cos(theta),r.*sin(theta)).*r;
rmax = @(theta) 1./(sin(theta) + cos(theta));
Q = guad2d(polarfun,0,pi/2,0,rmax)
```


Limitations

quad2d begins by mapping the region of integration to a rectangle. Consequently, it may have trouble integrating over a region that does not have four sides or has a side that cannot be mapped smoothly to a straight line. If the integration is unsuccessful, some helpful tactics are leaving Singular set to its default value of true, changing between Cartesian and polar coordinates, or breaking the region of integration into pieces and adding the results of integration over the pieces.


For example:

```
fun = @(x,y)abs(x.^2 + y.^2 - 0.25);
c = @(x)-sqrt(1 - x.^2);
d = @(x)sqrt(1 - x.^2);
quad2d(fun,-1,1,c,d,'AbsTol',1e-8,...
'FailurePlot',true,'Singular',false)
Warning: Reached the maximum number of function ...
evaluations (2000). The result fails the ...
global error test.
```

The failure plot shows two areas of difficulty, near the points (-1,0) and (1,0) and near the circle $x^2 + y^2 = 0.25$:



Changing the value of Singular to true will cope with the geometric singularities at (-1,0) and (1,0). The larger shaded areas may need refinement but are probably not areas of difficulty.




From here you can take advantage of symmetry:

Q = 4*quad2d(fun,0,1,0,d,'Abstol',1e-8,... 'Singular',true, 'FailurePlot',true)

However, the code is still working very hard near the singularity. It may not be able to provide higher accuracy:

Q = 4*quad2d(fun,0,1,0,d,'Abstol',1e-10,... 'Singular',true,'FailurePlot',true) Warning: Reached the maximum number of function ... evaluations (2000). The result passes the ... global error test.



At higher accuracy, a change in coordinates may work better.

polarfun = @(theta,r) fun(r.*cos(theta),r.*sin(theta)).*r; Q = 4*quad2d(polarfun,0,pi/2,0,1,'AbsTol',1e-10)

It is best to put the singularity on the boundary by splitting the region of integration into two parts:

Q1 = 4*quad2d(polarfun,0,pi/2,0,0.5,'AbsTol',5e-11); Q2 = 4*quad2d(polarfun,0,pi/2,0.5,1,'AbsTol',5e-11); Q = Q1 + Q2

References [1] L.F. Shampine "Vectorized Adaptive Quadrature in MATLAB," *Journal of Computational and Applied Mathematics*, 211, 2008, pp.131–140.

See Also dblquad, quad, quadl, quadv, quadgk, triplequad, function_handle (@), "Anonymous Functions"

Purpose	Numerically evaluate integral, adaptive Gauss-Kronrod quadrature
Syntax	q = quadgk(fun,a,b) [q,errbnd] = quadgk(fun,a,b) [q,errbnd] = quadgk(fun,a,b,param1,val1,param2,val2,)
Description	q = quadgk(fun,a,b) attempts to approximate the integral of a scalar-valued function fun from a to b using high-order global adaptive quadrature and default error tolerances. The function $y = fun(x)$ should accept a vector argument x and return a vector result y, where y is the integrand evaluated at each element of x. fun must be a function handle. See "Function Handles" in the MATLAB Programming documentation for more information. Limits a and b can be -Inf or Inf. If both are finite, they can be complex. If at least one is complex, the integral is approximated over a straight line path from a to b in the complex plane.
	"Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide additional parameters to the function fun, if necessary.
	[q,errbnd] = quadgk(fun,a,b) returns an approximate upper bound on the absolute error, $ Q - I $, where I denotes the exact value of the integral.
	<pre>[q,errbnd] = quadgk(fun,a,b,param1,val1,param2,val2,) performs the integration with specified values of optional parameters. The available parameters are</pre>

Parameter	Description	
'AbsTol'	Absolute error tolerance.	quadgk attempts to satisfy
	The default value of 'AbsTol' is 1.e-10 (double), 1.e-5 (single).	errbnd <= max(AbsTol,R This is absolute error control when Q is sufficiently small and relative error control
'RelTol'	Relative error tolerance.	when Q is larger. For pure absolute error
	The default value of 'RelTol' is 1.e-6 (double), 1.e-4 (single).	<pre>control use 'AbsTol' > 0 and 'RelTol'= 0. For pure relative error control use 'AbsTol' = 0. Except when using pure absolute error control, the minimum relative tolerance is 'RelTol' >= 100*eps(cl</pre>
'Waypoints'	Vector of integration waypoints.	If fun(x) has discontinuities in the interval of integration, the locations should be supplied as a Waypoints vector. When a, b, and the waypoints are all real, only the waypoints between a and b are used, and they are used in sorted order. Note that waypoints are not intended for singularities in fun(x). Singular points should be handled by making them endpoints of separate

Parameter	Description	
		integrations and adding the results.
		If a, b, or any entry of the waypoints vector is complex, the integration is performed over a sequence of straight line paths in the complex plane, from a to the first waypoint, from the first waypoint to the second, and so forth, and finally from the last waypoint to b.
'MaxIntervalCou	Maximum number of intervals allowed. The default value is 650.	The 'MaxIntervalCount' parameter limits the number of intervals that quadgk uses at any one time after the first iteration. A warning is issued if quadgk returns early because of this limit. Routinely increasing this value is not recommended, but it may be appropriate when errbnd is small enough that the desired accuracy has nearly been achieved.

The list below contains information to help you determine which quadrature function in MATLAB to use:

- The quad function may be most efficient for low accuracies with nonsmooth integrands.
- The quad1 function may be more efficient than quad at higher accuracies with smooth integrands.
- The quadgk function may be most efficient for high accuracies and oscillatory integrands. It supports infinite intervals and can handle moderate singularities at the endpoints. It also supports contour integration along piecewise linear paths.
- The quadv function vectorizes quad for an array-valued fun.
- If the interval is infinite, [a, Inf), then for the integral of fun(x) to exist, fun(x) must decay as x approaches infinity, and quadgk requires it to decay rapidly. Special methods should be used for oscillatory functions on infinite intervals, but quadgk can be used if fun(x) decays fast enough.
- The quadgk function will integrate functions that are singular at finite endpoints if the singularities are not too strong. For example, it will integrate functions that behave at an endpoint c like log|x-c| or |x-c|^p for p >= -1/2. If the function is singular at points inside (a,b), write the integral as a sum of integrals over subintervals with the singular points as endpoints, compute them with quadgk, and add the results.

Examples Integrand with a singularity at an integration end point

Write an function myfun that computes the integrand:

function y = myfun(x)
y = exp(x).*log(x);

Then pass @myfun, a function handle to myfun, to quadgk, along with the limits of integration, 0 to 1:

```
Q = quadgk(@myfun, 0, 1)
```

Q =

-1.3179

Alternatively, you can pass the integrand to quadgk as an anonymous function handle F:

F = (@(x)exp(x).*log(x)); Q = quadgk(F,0,1);

Oscillatory integrand on a semi-infinite interval

Integrate over a semi-infinite interval with specified tolerances, and return the approximate error bound:

```
[q,errbnd] = quadgk(@(x)x.^5.*exp(-x).*sin(x),0,inf,'RelTol',1e-8,'
q =
    -15.0000
errbnd =
    9.4386e-009
```

Contour integration around a pole

Use Waypoints to integrate around a pole using a piecewise linear contour:

```
Q = quadgk(@(z)1./(2*z - 1),-1-i,-1-i,'Waypoints',[1-i,1+i,-1+i])
Q =
0.0000 + 3.1416i
```

Algorithm quadgk implements adaptive quadrature based on a Gauss-Kronrod pair (15th and 7th order formulas).

Diagnostics	quadgk may issue one of the following warnings:
	'Minimum step size reached' indicates that interval subdivision has produced a subinterval whose length is on the order of roundoff error in the length of the original interval. A nonintegrable singularity is possible.
	'Reached the limit on the maximum number of intervals in use' indicates that the integration was terminated before meeting the tolerance requirements and that continuing the integration would require more than MaxIntervalCount subintervals. The integral may not exist, or it may be difficult to approximate numerically. Increasing MaxIntervalCount usually does not help unless the tolerance requirements were nearly met when the integration was previously terminated.
	'Infinite or Not-a-Number function value encountered' indicates a floating point overflow or division by zero during the evaluation of the integrand in the interior of the interval.
References	[1] L.F. Shampine "Vectorized Adaptive Quadrature in MATLAB," Journal of Computational and Applied Mathematics, 211, 2008, pp.131–140.
See Also	quad2d, dblquad, quad, quadl, quadv, triplequad, function_handle (@), "Anonymous Functions"

Purpose	Numerically evaluate integral, adaptive Lobatto quadrature
Syntax	<pre>q = quadl(fun,a,b) q = quadl(fun,a,b,tol) quadl(fun,a,b,tol,trace) [q,fcnt] = quadl()</pre>
Description	q = quadl(fun,a,b) approximates the integral of function fun from a to b, to within an error of 10^{-6} using recursive adaptive Lobatto quadrature. fun is a function handle. See "Function Handles" in the MATLAB Programming documentation for more information. fun accepts a vector x and returns a vector y, the function fun evaluated at each element of x. Limits a and b must be finite.
	"Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide additional parameters to the function fun, if necessary.
	q = quadl(fun,a,b,tol) uses an absolute error tolerance of tol instead of the default, which is 1.0e-6. Larger values of tol result in fewer function evaluations and faster computation, but less accurate results.
	quadl(fun,a,b,tol,trace) with non-zero trace shows the values of [fcnt a b-a q] during the recursion.
	[q,fcnt] = quadl() returns the number of function evaluations.
	Use array operators $.*, ./$ and $.^$ in the definition of fun so that it can be evaluated with a vector argument.
	The function quad may be more efficient with low accuracies or nonsmooth integrands.
	The list below contains information to help you determine which quadrature function in MATLAB to use:
	• The quad function may be most efficient for low accuracies with nonsmooth integrands.

	• The quad1 function may be more efficient than quad at higher accuracies with smooth integrands.
	• The quadgk function may be most efficient for high accuracies and oscillatory integrands. It supports infinite intervals and can handle moderate singularities at the endpoints. It also supports contour integration along piecewise linear paths.
	• The quadv function vectorizes quad for an array-valued fun.
	• If the interval is infinite, [a, Inf), then for the integral of fun(x) to exist, fun(x) must decay as x approaches infinity, and quadgk requires it to decay rapidly. Special methods should be used for oscillatory functions on infinite intervals, but quadgk can be used if fun(x) decays fast enough.
	 The quadgk function will integrate functions that are singular at finite endpoints if the singularities are not too strong. For example, it will integrate functions that behave at an endpoint c like log x-c or x-c ^p for p >= -1/2. If the function is singular at points inside (a,b), write the integral as a sum of integrals over subintervals with the singular points as endpoints, compute them with quadgk, and add the results.
Examples	Pass M-file function handle @myfun to quad1:
	<pre>Q = quadl(@myfun,0,2);</pre>
	where the M-file myfun.m is
	<pre>function y = myfun(x) y = 1./(x.^3-2*x-5);</pre>
	Pass anonymous function handle F to quad1:
	<pre>F = @(x) 1./(x.^3-2*x-5); Q = quadl(F,0,2);</pre>

Algorithm quad1 implements a high order method using an adaptive Gauss/Lobatto quadrature rule.

Diagnostics	quad1 may issue one of the following warnings:
	'Minimum step size reached' indicates that the recursive interval subdivision has produced a subinterval whose length is on the order of roundoff error in the length of the original interval. A nonintegrable singularity is possible.
	'Maximum function count exceeded' indicates that the integrand has been evaluated more than 10,000 times. A nonintegrable singularity is likely.
	'Infinite or Not-a-Number function value encountered' indicates a floating point overflow or division by zero during the evaluation of the integrand in the interior of the interval.
See Also	quad2d, dblquad, quad, quadgk, triplequad, function_handle (@), "Anonymous Functions"
References	[1] Gander, W. and W. Gautschi, "Adaptive Quadrature - Revisited," BIT, Vol. 40, 2000, pp. 84–101. This document is also available at http://www.inf.ethz.ch/personal/gander.

quadv

Purpose	Vectorized quadrature
Syntax	<pre>Q = quadv(fun,a,b) Q = quadv(fun,a,b,tol) Q = quadv(fun,a,b,tol,trace) [Q,fcnt] = quadv()</pre>
Description	Q = quadv(fun,a,b) approximates the integral of the complex array-valued function fun from a to b to within an error of 1.e-6 using recursive adaptive Simpson quadrature. fun is a function handle. See "Function Handles" in the MATLAB Programming documentation for more information. The function $Y = fun(x)$ should accept a scalar argument x and return an array result Y, whose components are the integrands evaluated at x. Limits a and b must be finite.
	"Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide addition parameters to the function fun, if necessary.
	Q = quadv(fun,a,b,tol) uses the absolute error tolerance tol for all the integrals instead of the default, which is 1.e-6.
	Note The same tolerance is used for all components, so the results obtained with quadv are usually not the same as those obtained with quad on the individual components.
	Q = quadv(fun,a,b,tol,trace) with non-zero trace shows the values of [fcnt a b-a Q(1)] during the recursion.
	[Q,fcnt] = quadv() returns the number of function evaluations.
	The list below contains information to help you determine which quadrature function in MATLAB to use:
	• The quad function may be most efficient for low accuracies with nonsmooth integrands.

- The quad1 function may be more efficient than quad at higher accuracies with smooth integrands.
- The quadgk function may be most efficient for high accuracies and oscillatory integrands. It supports infinite intervals and can handle moderate singularities at the endpoints. It also supports contour integration along piecewise linear paths.
- The quadv function vectorizes quad for an array-valued fun.
- If the interval is infinite, [a, Inf), then for the integral of fun(x) to exist, fun(x) must decay as x approaches infinity, and quadgk requires it to decay rapidly. Special methods should be used for oscillatory functions on infinite intervals, but quadgk can be used if fun(x) decays fast enough.
- The quadgk function will integrate functions that are singular at finite endpoints if the singularities are not too strong. For example, it will integrate functions that behave at an endpoint c like log|x-c| or |x-c|^p for p >= -1/2. If the function is singular at points inside (a,b), write the integral as a sum of integrals over subintervals with the singular points as endpoints, compute them with quadgk, and add the results.

Example For the parameterized array-valued function myarrayfun, defined by

function Y = myarrayfun(x,n) Y = 1./((1:n)+x);

the following command integrates myarrayfun, for the parameter value n = 10 between a = 0 and b = 1:

Qv = quadv(@(x)myarrayfun(x,10),0,1);

The resulting array Qv has 10 elements estimating Q(k) = log((k+1)./(k)), for k = 1:10.

The entries in Qv are slightly different than if you compute the integrals using quad in a loop:

```
for k = 1:10
  Qs(k) = quadv(@(x)myscalarfun(x,k),0,1);
end
where myscalarfun is:
  function y = myscalarfun(x,k)
  y = 1./(k+x);
quad, quad2d, quadgk, quad1, dblquad, triplequad, function_handle
```

See Also

(@)

Purpose	Create and open question dialog box	
Syntax	<pre>button = questdlg('qstring') button = questdlg('qstring','title') button = questdlg('qstring','title',default) button = questdlg('qstring','title','str1','str2',default) button = questdlg('qstring','title','str1','str2','str3',</pre>	
Description	<pre>button = questdlg('qstring') displays a modal dialog box presenting the question 'qstring'. The dialog has three default buttons, Yes, No, and Cancel. If the user presses one of these three buttons, button is set to the name of the button pressed. If the user presses the close button on the dialog without making a choice, button is set to the empty string. If the user presses the Return key, button is set to 'Yes'. 'qstring' is a cell array or a string that automatically wraps to fit within the dialog box.</pre>	
	Note A modal dialog box prevents the user from interacting with other windows before responding. For more information, see WindowStyle in the MATLAB Figure Properties.	
	<pre>button = questdlg('qstring','title') displays a question dialog with 'title' displayed in the dialog's title bar.</pre>	
	<pre>button = questdlg('qstring','title',default) specifies which</pre>	

push button is the default in the event that the **Return** key is pressed. 'default' must be 'Yes', 'No', or 'Cancel'.

button = questdlg('qstring','title','str1','str2',default)
creates a question dialog box with two push buttons labeled 'str1'
and 'str2'. default specifies the default button selection and must
be 'str1' or 'str2'.

button =

questdlg('qstring','title','str1','str2','str3',default)
creates a question dialog box with three push buttons labeled 'str1',
'str2', and 'str3'. default specifies the default button selection and
must be 'str1', 'str2', or 'str3'.

When *default* is specified, but is not set to one of the button names, pressing the **Enter** key displays a warning and the dialog remains open.

button = questdlg('qstring', 'title', ..., options) replaces the string *default* with a structure, options. The structure specifies which button string is the default answer, and whether to use TeX to interpret the question string, qstring. Button strings and dialog titles cannot use TeX interpretation. The options structure must include the fields Default and Interpreter, both strings. It can include other fields, but questdlg does not use them. You can set Interpreter to 'none' or 'tex'. If the Default field does not contain a valid button name, a command window warning is issued and the dialog box does not respond to pressing the **Enter** key.

Examples Example 1

Create a dialog that requests a dessert preference and encode the resulting choice as an integer.

```
% Construct a questdlg with three options
choice = questdlg('Please choose a dessert:', ...
'Dessert Menu', ...
'Ice cream','Cake','No thank you','No thank you');
% Handle response
switch choice
    case 'Ice cream'
        disp([choice ' coming right up.'])
        dessert = 1;
        break
    case 'Cake'
        disp([choice ' coming right up.'])
        dessert = 2;
        break
```

```
case 'No thank you'
  disp('I''ll bring you your check.')
  dessert = 0;
```

end



The case statements can contain white space but are case-sensitive.

Example 2

Specify an options structure to use the TeX interpreter to format a question.

```
options.Interpreter = 'tex';
% Include the desired Default answer
options.Default = 'Don''t know';
% Create a TeX string for the question
qstring = 'Is \Sigma(\alpha - \beta) < 0?';
choice = questdlg(qstring, 'Boundary Condition',...
'Yes', 'No', 'Don''t know', options)
```

🛃 B	📣 Boundary Condition		
	? Ιs Σία · β	i) < 0?	
	Yes	No	Don't know

questdlg

See Also dialog, errordlg, helpdlg, inputdlg, listdlg, msgbox, warndlg figure, textwrap, uiwait, uiresume Predefined Dialog Boxes for related functions

Purpose	Terminate MATLAB program
GUI Alternatives	As an alternative to the quit function, use the Close box or select File > Exit MATLAB in the MATLAB desktop.
Syntax	quit quit cancel quit force
Description	quit displays a confirmation dialog box if the confirm upon quitting preference is selected, and if confirmed or if the confirmation preference is not selected, terminates MATLAB after running finish.m, if finish.m exists. The workspace is not automatically saved by quit. To save the workspace or perform other actions when quitting, create a finish.m file to perform those actions. For example, you can display a custom dialog box to confirm quitting using a finish.m file—see the following examples for details. If an error occurs while finish.m file without losing your workspace.
	quit cancel is for use in finish.m and cancels quitting. It has no effect anywhere else.
	quit force bypasses finish.m and terminates MATLAB. Use this to override finish.m, for example, if an errant finish.m will not let you quit.
Remarks	When using Handle Graphics objects in finish.m, use uiwait, waitfor, or drawnow so that figures are visible. See the reference pages for these functions for more information.
	If you want MATLAB to display the following confirmation dialog box after running quit, select File > Preferences > General > Confirmation Dialogs . Then select the check box for Confirm before exiting MATLAB, and click OK .



Examples Two sample finish.m files are included with MATLAB. Use them to help you create your own finish.m, or rename one of the files to finish.m to use it.

- finishsav.m—Saves the workspace to a MAT-file when MATLAB quits.
- finishdlg.m—Displays a dialog allowing you to cancel quitting; it uses quit cancel and contains the following code:

```
button = questdlg('Ready to quit?', ...
    'Exit Dialog','Yes','No','No');
switch button
    case 'Yes',
    disp('Exiting MATLAB');
    %Save variables to matlab.mat
    save
    case 'No',
    quit cancel;
end
```

See Also exit, finish, save, startup

Purpose Terminate MATLAB Automation set	erver
--	-------

Syntax MATLAB Client

h.Quit Quit(h) invoke(h, '**Quit**')

IDL Method Signature

void Quit(void)

Microsoft Visual Basic Client Quit

duit

Description Quit terminates the MATLAB server session attached to handle h.

Remarks Server function names, like Quit, are case sensitive when using the first syntax shown.

There is no difference in the operation of the three syntaxes shown above for the MATLAB client.

quiver

Purpose Quiver or velocity plot



GUI Alternatives To graph selected variables, use the Plot Selector Implot(t,y) Implot(t,y) Imploted the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in *plot edit* mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.

Syntax quiver(x,y,u,v)
quiver(u,v)
quiver(...,scale)
quiver(...,LineSpec)
quiver(...,LineSpec,'filled')
quiver(axes_handle,...)
h = quiver(...)

Description A quiver plot displays velocity vectors as arrows with components (u, v) at the points (x, y).

For example, the first vector is defined by components u(1),v(1) and is displayed at the point x(1),y(1).

quiver (x, y, u, v) plots vectors as arrows at the coordinates specified in each corresponding pair of elements in x and y. The matrices x, y, u, and v must all be the same size and contain corresponding position and velocity components. However, x and y can also be vectors, as explained in the next section. By default, the arrows are scaled to just not overlap, but you can scale them to be longer or shorter if you want.

Expanding x- and y-Coordinates

MATLAB expands x and y if they are not matrices. This expansion is equivalent to calling meshgrid to generate matrices from vectors:

[x,y] = meshgrid(x,y); quiver(x,y,u,v)

In this case, the following must be true:

length(x) = n and length(y) = m, where [m,n] = size(u) = size(v).

The vector x corresponds to the columns of u and v, and vector y corresponds to the rows of u and v.

quiver(u,v) draws vectors specified by u and v at equally spaced points in the x-y plane.

quiver(..., scale) automatically scales the arrows to fit within the grid and then stretches them by the factor scale. scale = 2 doubles their relative length, and scale = 0.5 halves the length. Use scale = 0 to plot the velocity vectors without automatic scaling. You can also tune the length of arrows after they have been drawn by choosing the **Plot**

Edit tool, selecting the quivergroup object, opening the Property Editor, and adjusting the Length slider.

quiver(...,LineSpec) specifies line style, marker symbol, and color using any valid LineSpec. quiver draws the markers at the origin of the vectors.

quiver(...,LineSpec, 'filled') fills markers specified by LineSpec.


quiver(axes_handle,...) plots into the axes with the handle axes_handle instead of into the current axes (gca).

h = quiver(...) returns the handle to the quivergroup object.

Examples Showing the Gradient with Quiver Plots

Plot the gradient field of the function $z = xe^{(-x^2 - y^2)}$:

[X,Y] = meshgrid(-2:.2:2); Z = X.*exp(-X.^2 - Y.^2); [DX,DY] = gradient(Z,.2,.2); contour(X,Y,Z) hold on



See Also contour, LineSpec, plot, quiver3 "Direction and Velocity Plots" on page 1-99 for related functions Two-Dimensional Quiver Plots for more examples Quivergroup Properties for property descriptions


Purpose	3-D quiver or velocity plot
---------	-----------------------------



GUI Alternatives	To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.
Syntax	<pre>quiver3(x,y,z,u,v,w) quiver3(z,u,v,w) quiver3(,scale) quiver3(,LineSpec) quiver3(,LineSpec,'filled') quiver3(axes_handle,) h = quiver3()</pre>
Description	A three-dimensional quiver plot displays vectors with components (u,v,w) at the points (x,y,z) , where u,v,w,x,y , and z all have real (non-complex) values. quiver3(x,y,z,u,v,w) plots vectors with components (u,v,w) at the points (x,y,z) . The matrices x,y,z,u,v,w must all be the same size and contain the corresponding position and vector components.
	quiver3(z,u,v,w) plots the vectors at the equally spaced surface points specified by matrix z. quiver3 automatically scales the vectors based on the distance between them to prevent them from overlapping.
	quiver3(,scale) automatically scales the vectors to prevent them from overlapping, and then multiplies them by scale. scale = 2 doubles their relative length, and scale = 0.5 halves them. Use scale = 0 to plot the vectors without the automatic scaling.

	<pre>quiver3(,LineSpec) specifies line type and color using any valid LineSpec.</pre>
	<pre>quiver3(,LineSpec,'filled') fills markers specified by LineSpec.</pre>
	quiver3(axes_handle,) plots into the axes with the handle axes_handle instead of into the current axes (gca).
	h = quiver3() returns a vector of line handles.
Examples	Plot the surface normals of the function $z = xe^{(-x^2 - y^2)}$.
	[X,Y] = meshgrid(-2:0.25:2,-1:0.2:1);
	Z = X.* exp(-X.^2 - Y.^2); [U,V,W] = surfnorm(X,Y,Z);
	quiver3(X,Y,Z,U,V,W,0.5);
	hold on
	<pre>surf(X,Y,Z);</pre>
	colormap hsv
	view(-35,45) axis ([-2 2 -1 16 .6])
	hold off

quiver3



See Also axis, contour, LineSpec, plot, plot3, quiver, surfnorm, view "Direction and Velocity Plots" on page 1-99 for related functions Three-Dimensional Quiver Plots for more examples

Quivergroup Properties

Purpose	Define quivergroup prop	erties	
Modifying Properties	You can set and query graphics object properties using the set and get commands or the Property Editor (propertyeditor).		
-	Note that you cannot def	ine default properties for areaseries objects.	
	See Plot Objects for more	e information on quivergroup objects.	
Quivergroup Property Descriptions	This section provides a de default values.	escription of properties. Curly braces {} enclose	
	Annotation hg.Annotation object Read Only		
	Control the display of quivergroup objects in legends. The Annotation property enables you to specify whether this quivergroup object is represented in a figure legend.		
	hg.Annotation obj	tation property returns the handle of an lect. The hg.Annotation object has a property rmation, which contains an hg.LegendEntry	
	set its IconDispla	ained the hg.LegendEntry object, you can yStyle property to control whether the is displayed in a figure legend:	
	IconDisplayStyle Value	Purpose	
	on	Include the quivergroup object in a legend as one entry, but not its children objects	
	off	Do not include the quivergroup or its children in a legend (default)	
	children	Include only the children of the quivergroup as separate entries in the legend	

Setting the IconDisplayStyle Property

These commands set the IconDisplayStyle of a graphics object with handle hobj to children, which causes each child object to have an entry in the legend:

```
hAnnotation = get(hobj,'Annotation');
hLegendEntry = get(hAnnotation,'LegendInformation');
set(hLegendEntry,'IconDisplayStyle','children')
```

Using the IconDisplayStyle Property

See "Controlling Legends" for more information and examples.

AutoScale

{on} | off

Autoscale arrow length. Based on average spacing in the x and y directions, AutoScale scales the arrow length to fit within the grid-defined coordinate data and keeps the arrows from overlapping. After autoscaling, quiver applies the AutoScaleFactor to the arrow length.

AutoScaleFactor

scalar (default = 0.9)

User-specified scale factor. When AutoScale is on, the quiver function applies this user-specified autoscale factor to the arrow length. A value of 2 doubles the length of the arrows; 0.5 halves the length.

BeingDeleted

on | {off} Read Only

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions might not need to perform actions on objects if the objects are going to be deleted, and therefore, can check the object's BeingDeleted property before acting.

```
BusyAction
```

cancel | {queue}

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callbacks. If there is a callback function executing, callbacks invoked subsequently always attempt to interrupt it.

If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are

- cancel Discard the event that attempted to execute a second callback routine.
- queue Queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn

string or function handle

Button press callback function. A callback that executes whenever you press a mouse button while the pointer is over this object, but not over another graphics object. See the HitTestArea property for information about selecting objects of this type. See the figure's SelectionType property to determine if modifier keys were also pressed.

This property can be

- A string that is a valid MATLAB expression
- The name of a MATLAB file
- A function handle

Set this property to a function handle that references the callback. The expressions execute in the MATLAB workspace.

See "Function Handle Callbacks" for information on how to use function handles to define the callbacks.

Children

array of graphics object handles

Children of the quivergroup object. An array containing the handles of all line objects parented to this object (whether visible or not).

If a child object's HandleVisibility property is callback or off, its handle does not show up in this object's Children property. If you want the handle in the Children property, set the root ShowHiddenHandles property to on. For example:

set(0,'ShowHiddenHandles','on')

Clipping

{on} | off

Clipping mode. MATLAB clips graphs to the axes plot box by default. If you set Clipping to off, portions of graphs can be displayed outside the axes plot box. This can occur if you create a plot object, set hold to on, freeze axis scaling (axis manual), and then create a larger plot object.

Color

ColorSpec

Color of the object. A three-element RGB vector or one of the MATLAB predefined names, specifying the object's color.

See the ColorSpec reference page for more information on specifying color.

CreateFcn

string or function handle

Callback routine executed during object creation. This property defines a callback that executes when MATLAB creates an object. You must specify the callback during the creation of the object. For example,

graphicfcn(y, 'CreateFcn',@CallbackFcn)

where @*CallbackFcn* is a function handle that references the callback function and *graphicfcn* is the plotting function which creates this object.

MATLAB executes this routine after setting all other object properties. Setting this property on an existing object has no effect.

The handle of the object whose CreateFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DeleteFcn

string or function handle

Callback executed during object deletion. A callback that executes when this object is deleted (e.g., this might happen when you issue a delete command on the object, its parent axes, or the figure containing it). MATLAB executes the callback before destroying the object's properties so the callback routine can query these values.

The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which can be queried using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

See the BeingDeleted property for related information.

DisplayName

string (default is empty string)

String used by legend for this quivergroup object. The legend function uses the string defined by the DisplayName property to label this quivergroup object in the legend.

- If you specify string arguments with the legend function, DisplayName is set to this quivergroup object's corresponding string and that string is used for the legend.
- If DisplayName is empty, legend creates a string of the form, ['data' n], where n is the number assigned to the object based on its location in the list of legend entries. However, legend does not set DisplayName to this string.
- If you edit the string directly in an existing legend, DisplayName is set to the edited string.
- If you specify a string for the DisplayName property and create the legend using the figure toolbar, then MATLAB uses the string defined by DisplayName.

• To add programmatically a legend that uses the DisplayName string, call legend with the toggle or show option.

See "Controlling Legends" for more examples.

EraseMode

{normal} | none | xor | background

Erase mode. This property controls the technique MATLAB uses to draw and erase objects and their children. Alternative erase modes are useful for creating animated sequences, where control of the way individual objects are redrawn is necessary to improve performance and obtain the desired effect.

- normal Redraw the affected region of the display, performing the three-dimensional analysis necessary to ensure that all objects are rendered correctly. This mode produces the most accurate picture, but is the slowest. The other modes are faster, but do not perform a complete redraw and are therefore less accurate.
- none Do not erase objects when they are moved or destroyed. While the objects are still visible on the screen after erasing with EraseMode none, you cannot print these objects because MATLAB stores no information about their former locations.
- xor Draw and erase the object by performing an exclusive OR (XOR) with each pixel index of the screen behind it. Erasing the object does not damage the color of the objects behind it. However, the color of the erased object depends on the color of the screen behind it and it is correctly colored only when it is over the axes background color (or the figure background color if the axes Color property is set to none). That is, it isn't erased correctly if there are objects behind it.
- background Erase the graphics objects by redrawing them in the axes background color, (or the figure background color if the axes Color property is set to none). This damages other

graphics objects that are behind the erased object, but the erased object is always properly colored.

Printing with Nonnormal Erase Modes

MATLAB always prints figures as if the EraseMode of all objects is normal. This means graphics objects created with EraseMode set to none, xor, or background can look different on screen than on paper. On screen, MATLAB can mathematically combine layers of colors (e.g., performing an XOR on a pixel color with that of the pixel behind it) and ignore three-dimensional sorting to obtain greater rendering speed. However, these techniques are not applied to the printed output.

Set the axes background color with the axes Color property. Set the figure background color with the figure Color property.

You can use the MATLAB getframe command or other screen capture applications to create an image of a figure containing nonnormal mode objects.

HandleVisibility

{on} | callback | off

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally accessing objects that you need to protect for some reason.

- on Handles are always visible when HandleVisibility is on.
- callback Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have access to object handles.

• off — Setting HandleVisibility to off makes handles invisible at all times. This might be necessary when a callback invokes a function that might potentially damage the GUI (such as evaluating a user-typed string) and so temporarily hides its own handles during the execution of that function.

Functions Affected by Handle Visibility

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close.

Properties Affected by Handle Visibility

When a handle's visibility is restricted using callback or off, the object's handle does not appear in its parent's Children property, figures do not appear in the root's CurrentFigure property, objects do not appear in the root's CallbackObject property or in the figure's CurrentObject property, and axes do not appear in their parent's CurrentAxes property.

Overriding Handle Visibility

You can set the root ShowHiddenHandles property to on to make all handles visible regardless of their HandleVisibility settings (this does not affect the values of the HandleVisibility properties). See also findall.

Handle Validity

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties and pass it to any function that operates on handles.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

HitTest

{on} | off

Selectable by mouse click. HitTest determines whether this object can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click on the objects that compose the area graph. If HitTest is off, clicking this object selects the object below it (which is usually the axes containing it).

HitTestArea

on | {off}

Select the object by clicking lines or area of extent. This property enables you to select plot objects in two ways:

- Select by clicking lines or markers (default).
- Select by clicking anywhere in the extent of the plot.

When HitTestArea is off, you must click the object's lines or markers (excluding the baseline, if any) to select the object. When HitTestArea is on, you can select this object by clicking anywhere within the extent of the plot (i.e., anywhere within a rectangle that encloses it).

Interruptible

{on} | off

Callback routine interruption mode. The Interruptible property controls whether an object's callback can be interrupted by callbacks invoked subsequently.

Only callbacks defined for the ButtonDownFcn property are affected by the Interruptible property. MATLAB checks for events that can interrupt a callback only when it encounters a drawnow, figure, getframe, or pause command in the routine. See the BusyAction property for related information.

Setting Interruptible to on allows any graphics object's callback to interrupt callback routines originating from a bar property. Note that MATLAB does not save the state of variables or the display (e.g., the handle returned by the gca or gcf command) when an interruption occurs.

LineStyle

{-} | -- | : | -. | none

Line style. This property specifies the line style of the object. Available line styles are shown in the following table.

Specifier String	Line Style
-	Solid line (default)
	Dashed line
:	Dotted line
	Dash-dot line
none	No line

You can use LineStyle none when you want to place a marker at each point but do not want the points connected with a line (see the Marker property).

LineWidth

scalar

The width of linear objects and edges of filled areas. Specify this value in points (1 point = $1/_{72}$ inch). The default LineWidth is 0.5 points.

Marker

character (see table)

Marker symbol. The Marker property specifies the type of markers that are displayed at plot vertices. You can set values for the Marker property independently from the LineStyle property. Supported markers include those shown in the following table.

Marker Specifier	Description
+	Plus sign
0	Circle
*	Asterisk
	Point
х	Cross
S	Square
d	Diamond
^	Upward-pointing triangle
v	Downward-pointing triangle
>	Right-pointing triangle
<	Left-pointing triangle
р	Five-pointed star (pentagram)
h	Six-pointed star (hexagram)
none	No marker (default)

MarkerEdgeColor

ColorSpec | none | {auto}

Marker edge color. The color of the marker or the edge color for filled markers (circle, square, diamond, pentagram, hexagram, and the four triangles). ColorSpec defines the color to use. none specifies no color, which makes nonfilled markers invisible. auto sets MarkerEdgeColor to the same color as the Color property.

MarkerFaceColor

ColorSpec | {none} | auto

Marker face color. The fill color for markers that are closed shapes (circle, square, diamond, pentagram, hexagram, and the four triangles). ColorSpec defines the color to use. none makes the interior of the marker transparent, allowing the background to show through. auto sets the fill color to the axes color, or to the figure color if the axes Color property is set to none (which is the factory default for axes objects).

MarkerSize

size in points

Marker size. A scalar specifying the size of the marker in points. The default value for MarkerSize is 6 points (1 point = 1/72 inch). Note that MATLAB draws the point marker (specified by the '.' symbol) at one-third the specified size.

MaxHeadSize

scalar (default = 0.2

Maximum size of arrowhead. A value determining the maximum size of the arrowhead relative to the length of the arrow.

Parent

handle of parent axes, hggroup, or hgtransform

Parent of this object. This property contains the handle of the object's parent. The parent is normally the axes, hggroup, or hgtransform object that contains the object.

See "Objects That Can Contain Other Objects" for more information on parenting graphics objects.

Selected

on | {off}

Is object selected? When you set this property to on, MATLAB displays selection "handles" at the corners and midpoints if the SelectionHighlight property is also on (the default). You can, for example, define the ButtonDownFcn callback to set this property to on, thereby indicating that this particular object is selected. This property is also set to on when an object is manually selected in plot edit mode.

SelectionHighlight

{on} | off

Objects are highlighted when selected. When the Selected property is on, MATLAB indicates the selected state by drawing four edge handles and four corner handles. When SelectionHighlight is off, MATLAB does not draw the handles except when in plot edit mode and objects are selected manually.

ShowArrowHead

{on} | off

Display arrowheads on vectors. When this property is on, MATLAB draws arrowheads on the vectors displayed by quiver. When you set this property to off, quiver draws the vectors as lines without arrowheads.

Тад

 string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when you are constructing interactive graphics programs that would otherwise need to define object handles as

global variables or pass them as arguments between callbacks. You can define Tag as any string.

For example, you might create an areaseries object and set the Tag property.

```
t = area(Y, 'Tag', 'area1')
```

When you want to access objects of a given type, you can use findobj to find the object's handle. The following statement changes the FaceColor property of the object whose Tag is area1.

```
set(findobj('Tag', 'area1'), 'FaceColor', 'red')
```

Туре

string (read only)

Type of graphics object. This property contains a string that identifies the class of the graphics object. For stem objects, Type is 'hggroup'. This statement finds all the hggroup objects in the current axes.

```
t = findobj(gca,'Type','hggroup');
```

UIContextMenu

handle of a uicontextmenu object

Associate a context menu with this object. Assign this property the handle of a uicontextmenu object created in the object's parent figure. Use the uicontextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click over the object.

UserData

array

User-specified data. This property can be any data you want to associate with this object (including cell arrays and structures).

The object does not set values for this property, but you can access it using the set and get functions.

Visible

{on} | off

Visibility of this object and its children. By default, a new object's visibility is on. This means all children of the object are visible unless the child object's Visible property is set to off. Setting an object's Visible property to off prevents the object from being displayed. However, the object still exists and you can set and query its properties.

UData

matrix

One dimension of 2-D or 3-D vector components. UData, VData, and WData, together specify the components of the vectors displayed as arrows in the quiver graph. For example, the first vector is defined by components UData(1),VData(1),WData(1).

UDataSource

string (MATLAB variable)

Link UData to MATLAB variable. Set this property to a MATLAB variable that, by default, is evaluated in the base workspace to generate the UData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change UData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to return data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

VData

matrix

One dimension of 2-D or 3-D vector components. UData, VData and WData (for 3-D) together specify the components of the vectors displayed as arrows in the quiver graph. For example, the first vector is defined by components UData(1),VData(1),WData(1).

VDataSource

string (MATLAB variable)

Link VData to MATLAB variable. Set this property to a MATLAB variable that, by default, is evaluated in the base workspace to generate the VData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change VData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to return data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

WData

matrix

One dimension of 2-D or 3-D vector components. UData, VData and WData (for 3-D) together specify the components of the vectors displayed as arrows in the quiver graph. For example, the first vector is defined by components UData(1),VData(1),WData(1).

WDataSource

string (MATLAB variable)

Link WData to MATLAB variable. Set this property to a MATLAB variable that, by default, is evaluated in the base workspace to generate the WData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change WData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to return data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

XData

vector or matrix

X-axis coordinates of arrows. The quiver function draws an individual arrow at each x-axis location in the XData array.XData can be either a matrix equal in size to all other data properties or for 2-D, a vector equal in length to the number of columns in UData or VData. That is, length(XData) == size(UData,2).

If you do not specify XData (i.e., the input argument X), the quiver function uses the indices of UData to create the quiver graph. See the XDataMode property for related information.

XDataMode

{auto} | manual

Use automatic or user-specified x-axis values. If you specify XData (by setting the XData property or specifying the input argument X), the quiver function sets this property to manual.

If you set XDataMode to auto after having specified XData, the quiver function resets the *x* tick-mark labels to the indices of the U, V, and W data, overwriting any previous values.

XDataSource

string (MATLAB variable)

Link XData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the XData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change XData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

YData

vector or matrix

Y-axis coordinates of arrows. The quiver function draws an individual arrow at each y-axis location in the YData array. YData can be either a matrix equal in size to all other data properties or for 2-D, a vector equal in length to the number of rows in UData or VData. That is, length(YData) == size(UData,1).

If you do not specify YData (i.e., the input argument Y), the quiver function uses the indices of VData to create the quiver graph. See the YDataMode property for related information.

The input argument y in the quiver function calling syntax assigns values to YData.

YDataMode

{auto} | manual

Use automatic or user-specified y-axis values. If you specify YData (by setting the YData property or specifying the input argument Y), MATLAB sets this property to manual.

If you set YDataMode to auto after having specified YData, MATLAB resets the y tick-mark labels to the indices of the U, V, and W data, overwriting any previous values.

YDataSource

string (MATLAB variable)

Link YData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the YData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change YData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

ZData

vector or matrix

Z-axis coordinates of arrows. The quiver function draws an individual arrow at each z-axis location in the ZData array. ZData must be a matrix equal in size to XData and YData.

The input argument z in the quiver3 function calling syntax assigns values to ZData.

Purpose	QZ factorization for generalized eigenvalues
Syntax	[AA,BB,Q,Z] = qz(A,B) [AA,BB,Q,Z,V,W] = qz(A,B) qz(A,B,flag)
Description	The qz function gives access to intermediate results in the computation of generalized eigenvalues.
	[AA,BB,Q,Z] = qz(A,B) for square matrices A and B, produces upper quasitriangular matrices AA and BB, and unitary matrices Q and Z such that Q*A*Z = AA, and Q*B*Z = BB. For complex matrices, AA and BB are triangular.

[AA,BB,Q,Z,V,W] = qz(A,B) also produces matrices V and W whose columns are generalized eigenvectors.

qz(A,B,flag) for real matrices A and B, produces one of two decompositions depending on the value of flag:

'complex'	Produces a possibly complex decomposition with a triangular AA. For compatibility with earlier versions, 'complex' is the default.
'real'	Produces a real decomposition with a quasitriangular AA, containing 1-by-1 and 2-by-2 blocks on its diagonal.

If AA is triangular, the diagonal elements of AA and BB, $\alpha = \text{diag}(AA)$ and $\beta = \text{diag}(BB)$, are the generalized eigenvalues that satisfy

 $A * V * \beta = B * V * \alpha$ $\beta * W' * A = \alpha * W' * B$

The eigenvalues produced by

 $\lambda = \operatorname{eig}(A, B)$

are the ratios of the α s and β s.

$$\lambda = \alpha . / \beta$$

If AA is not triangular, it is necessary to further reduce the 2-by-2 blocks to obtain the eigenvalues of the full system.

See Also eig

rand

Purpose	Uniformly distributed pseudorandom numbers
Syntax	<pre>r = rand(n) rand(m,n) rand([m,n]) rand([m,n,p,) rand([m,n,p,]) rand rand(size(A)) r = rand(, 'double') r = rand(, 'single')</pre>
Description	<pre>r = rand(n) returns an n-by-n matrix containing pseudorandom values drawn from the standard uniform distribution on the open interval (0,1). rand(m,n) or rand([m,n]) returns an m-by-n matrix. rand(m,n,p,) or rand([m,n,p,]) returns an m-by-n-by-p-by array. rand returns a scalar. rand(size(A)) returns an array the same size as A.</pre>
	<pre>r = rand(, 'double') or r = rand(, 'single') returns an array of uniform values of the specified class.</pre>
	Note Note: The size inputs m, n, p, should be nonnegative integers. Negative integers are treated as 0.
	The sequence of numbers produced by rand is determined by the

The sequence of numbers produced by rand is determined by the internal state of the uniform pseudorandom number generator that underlies rand, randi, and randn. The default random number stream properties can be set using @RandStream methods. See @RandStream for details about controlling the default stream.

Resetting the default stream to the same fixed state allows computations to be repeated. Setting the stream to different states leads to unique computations, however, it does not improve any statistical properties. Since the random number generator is initialized to the same state every time MATLAB software starts up, rand, randn, and randi will

	generate the same sequence of numbers in each session until the state is changed.
	Note In versions of MATLAB prior to 7.7, you controlled the internal state of the random number stream used by rand by calling rand directly with the 'seed', 'state', or 'twister' keywords. That syntax is still supported for backwards compatibility, but is deprecated. For version 7.7, use the default stream as described in the @RandStream reference documentation.
Examples	Generate values from the uniform distribution on the interval $[a, b]$. r = a + (b-a).*rand(100,1);
	Replace the default stream at MATLAB startup, using a stream whose seed is based on clock, so that rand will return different values in different MATLAB sessions. It is usually not desirable to do this more than once per MATLAB session.
	RandStream.setDefaultStream (RandStream('mt19937ar','seed',sum(100*clock))); rand(1,5)
	Save the current state of the default stream, generate 5 values, restore the state, and repeat the sequence.
	defaultStream = RandStream.getDefaultStream; savedState = defaultStream.State; u1 = rand(1,5) defaultStream.State = savedState; u2 = rand(1,5) % contains exactly the same values as u1
See Also	randi, randn, @RandStream, rand (RandStream), getDefaultStream (RandStream), sprand, sprandn, randperm

rand (RandStream)

Purpose	Uniformly distributed random numbers
Class	@RandStream
Syntax	<pre>r = rand(s,n) rand(s,m,n) rand(s,[m,n]) rand(s,m,n,p,) rand(s,[m,n,p,]) rand(s) rand(s) rand(s,size(A)) r = rand(, 'double') r = rand(, 'single')</pre>
Description	r = rand(s,n) returns an n-by-n matrix containing pseudorandom values drawn from the standard uniform distribution on the open interval (0,1). The values are drawn from the random stream s. rand(s,m,n) or rand(s,[m,n]) returns an m-by-n matrix. rand(s,m,n,p,) or rand(s,[m,n,p,]) returns an m-by-n-by-p-by array. rand(s) returns a scalar. rand(s,size(A)) returns an array the same size as A. r = rand(, 'double') or $r = rand(, 'single')$ returns an array of uniform values of the specified class.
	Note The size inputs m, n, p, should be nonnegative integers. Negative integers are treated as 0.
	The sequence of numbers produced by rand is determined by the internal state of the random number stream 5. Bosetting that stream

The sequence of numbers produced by rand is determined by the internal state of the random number stream s. Resetting that stream to the same fixed state allows computations to be repeated. Setting the stream to different states leads to unique computations, however, it does not improve any statistical properties.

See Also rand, @RandStream, randi (RandStream), randn (RandStream), randperm (RandStream)

randi

Purpose	Uniformly distributed pseudorandom integers
Syntax	<pre>randi(imax) r = randi(imax,n) randi(imax,m,n) randi(imax,[m,n]) randi(imax,m,n,p,) randi(imax,[m,n,p,]) randi(imax,size(A)) r = randi([imin,imax],) r = randi(, classname)</pre>
Description	<pre>randi(imax) returns a random integer on the interval1:imax. r = randi(imax,n) returns an n-by-n matrix containing pseudorandom integer values drawn from the discrete uniform distribution on 1:imax. randi(imax,m,n) or randi(imax,[m,n]) returns an m-by-n matrix. randi(imax,m,n,p,) or randi(imax,[m,n,p,]) returns an m-by-n-by-p-by array. randi(imax,size(A)) returns an array the same size as A.</pre>
	<pre>r = randi([imin,imax],) returns an array containing integer values drawn from the discrete uniform distribution on imin:imax.</pre>
	r = randi(, classname) returns an array of integer values of class classname. classname does not support 64-bit integers.
	Note Note: The size inputs m, n, p, should be nonnegative integers. Negative integers are treated as 0.

The sequence of numbers produced by randi is determined by the internal state of the uniform pseudorandom number generator that underlies rand, randi, and randn. randi uses one uniform value from that default stream to generate each integer value. Control the default stream using its properties and methods. See <code>@RandStream</code> for details about the default stream.

	Resetting the default stream to the same fixed state allows computations to be repeated. Setting the stream to different states leads to unique computations, however, it does not improve any statistical properties. Since the random number generator is initialized to the same state every time MATLAB software starts up, rand, randn, and randi will generate the same sequence of numbers in each session until the state is changed.
Examples	Generate integer values from the uniform distribution on the set 1:10. r = randi(10,100,1);
	<pre>Generate an integer array of integers drawn uniformly from 1:10. r = randi(10,100,1,'uint32');</pre>
	Generate integer values drawn uniformly from -10:10. r = randi([-10 10],100,1);
	Replace the default stream at MATLAB startup, using a stream whose seed is based on clock, so that randi will return different values in different MATLAB sessions. It is usually not desirable to do this more than once per MATLAB session.
	RandStream.setDefaultStream (RandStream('mt19937ar','seed',sum(100*clock)));

randi(100,1,5)

Save the current state of the default stream, generate 5 integer values, restore the state, and repeat the sequence.

```
defaultStream = RandStream.getDefaultStream;
savedState = defaultStream.State;
i1 = randi(10,1,5)
defaultStream.State = savedState;
i2 = randi(10,1,5) %contains exactly the same values as i1
```

See Also rand, randn, @RandStream, randi (RandStream), getDefaultStream (RandStream)

Purpose	Uniformly distributed pseudorandom integers
Class	@RandStream
Syntax	<pre>r = randi(s,imax,n) randi(s,imax,m,n) randi(s,imax,[m,n]) randi(s,imax,m,n,p,) randi(s,imax,[m,n,p,]) randi(s,imax) randi(s,imax,size(A)) r = randi(s,[imin,imax],) r = randi(, classname)</pre>
Description	<pre>r = randi(s,imax,n) returns an n-by-n matrix containing pseudorandom integer values drawn from the discrete uniform distribution on 1:imax. randi draws those values from the random stream s. randi(s,imax,m,n) or randi(s,imax,[m,n]) returns an m-by-n matrix. randi(s,imax,m,n,p,) or randi(s,imax,[m,n,p,]) returns an m-by-n-by-p-by array. randi(s,imax) returns a scalar. randi(s,imax,size(A)) returns an array the same size as A.</pre>
	<pre>r = randi(s,[imin,imax],) returns an array containing integer values drawn from the discrete uniform distribution on imin:imax.</pre>
	r = randi(, classname) returns an array of integer values of class classname. classname does not support 64-bit integers.
	Note The size inputs m, n, p, should be nonnegative integers. Negative integers are treated as 0.

The sequence of numbers produced by randi is determined by the internal state of the random stream s. randi uses one uniform value from s to generate each integer value. Resetting s to the same fixed

state allows computations to be repeated. Setting the stream to different states leads to unique computations, however, it does not improve any statistical properties.

See Also rand, @RandStream, rand (RandStream), randn (RandStream), randperm (RandStream)

Purpose	Normally distributed pseudorandom numbers
Syntax	<pre>r = randn(n) randn(m,n) randn([m,n]) randn(m,n,p,) randn([m,n,p,]) randn(size(A)) r = randn(, 'double') r = randn(, 'single')</pre>
Description	r = randn(n) returns an n-by-n matrix containing pseudorandom values drawn from the standard normal distribution. randn(m,n) or randn([m,n]) returns an m-by-n matrix. randn(m,n,p,) or randn([m,n,p,]) returns an m-by-n-by-p-by array. randn returns a scalar. randn(size(A)) returns an array the same size as A. r = randn(, 'double') or $r = randn(, 'single')$ returns an array of normal values of the specified class.
	Note The size inputs m, n, p, should be nonnegative integers. Negative integers are treated as 0. The sequence of numbers produced by randn is determined by the internal state of the uniform pseudorandom number generator that
	underlies rand, randi, and randn. randn uses one or more uniform values from that default stream to generate each normal value. Control the default stream using its properties and methods. See @RandStream for details about the default stream.
	Resetting the default stream to the same fixed state allows computations to be repeated. Setting the stream to different states leads to unique computations, however, it does not improve any statistical properties.

Since the random number generator is initialized to the same state every time MATLAB software starts up, rand, randn, and randi will generate the same sequence of numbers in each session until the state is changed.

Note In versions of MATLAB prior to 7.7, you controlled the internal state of the random number stream used by randn by calling randn directly with the 'seed' or 'state' keywords. That syntax is still supported for backwards compatibility, but is deprecated. For version 7.7, use the default stream as described in the <code>@RandStream</code> reference documentation.

Examples Generate values from a normal distribution with mean 1 and standard deviation 2.

r = 1 + 2.*randn(100,1);

Generate values from a bivariate normal distribution with specified mean vector and covariance matrix.

```
mu = [1 2];
Sigma = [1 .5; .5 2]; R = chol(Sigma);
z = repmat(mu,100,1) + randn(100,2)*R;
```

Replace the default stream at MATLAB startup, using a stream whose seed is based on clock, so that randn will return different values in different MATLAB sessions. It is usually not desirable to do this more than once per MATLAB session.

```
RandStream.setDefaultStream ...
    (RandStream('mt19937ar','seed',sum(100*clock)));
randn(1,5)
```

Save the current state of the default stream, generate 5 values, restore the state, and repeat the sequence.

```
defaultStream = RandStream.getDefaultStream;
savedState = defaultStream.State;
```

z1 = randn(1,5)
defaultStream.State = savedState;
z2 = randn(1,5) % contains exactly the same values as z1
See Also
rand, randi, @RandStream, randn (RandStream), getDefaultStream
(RandStream)

Purpose	Normally distributed pseudorandom numbers
Class	@RandStream
Syntax	<pre>randn(s,m,n) randn(s,[m,n]) randn(s,m,n,p,) randn(s,[m,n,p,]) randn(s) randn(s,size(A)) r = randn(, 'double') r = randn(, 'single')</pre>
Description	<pre>r = randn(s,n) returns an n-by-n matrix containing pseudorandom values drawn from the standard normal distribution. randn draws those values from the random stream s. randn(s,m,n) or randn(s,[m,n]) returns an m-by-n matrix. randn(s,m,n,p,) or randn(s,[m,n,p,]) returns an m-by-n-by-p-by array. randn(s) returns a scalar. randn(s,size(A)) returns an array the same size as A. r = randn(, 'double') or r = randn(, 'single') returns an array of uniform values of the specified class.</pre>
	Note The size inputs m, n, p, should be nonnegative integers. Negative integers are treated as 0.
	The sequence of numbers produced by randn is determined by the internal state of the random stream s. randn uses one or more uniform values from s to generate each normal value. Resetting that stream to the same fixed state allows computations to be repeated. Setting the stream to different states leads to unique computations, however, it does not improve any statistical properties.
See Also	randn,@RandStream,rand (RandStream),randi (RandStream)

randperm

Purpose	Random permutation
Syntax	p = randperm(n)
Description	<pre>p = randperm(n) returns a random permutation of the integers 1:n.</pre>
Remarks	The randperm function calls rand and therefore changes the state of the default random number stream.
Examples	randperm(6) might be the vector [3 2 6 4 1 5]
	or it might be some other permutation of 1:6.
See Also	permute

Purpose	Random permutation
Class	@RandStream
Syntax	randperm(s,n)
Description	<pre>randperm(s,n) generates a random permutation of the integers from 1 to n. For example, randperm(s,6) might be [2 4 5 6 1 3]. randperm(s,n) uses random values drawn from the random number stream s.</pre>
See Also	permute, @RandStream

RandStream

Purpose Random number stream

Constructor RandStream (RandStream)

Description Pseudorandom numbers in MATLAB come from one or more random number streams. The simplest way to generate arrays of random numbers is to use rand, randn, or randi. These functions all rely on the same stream of uniform random numbers, known as the default stream. You can create other stream objects that act separately from the default stream, and you can use their rand, randi, or randn methods to generate arrays of random numbers. You can also create a random number stream and make it the default stream.

To create a single random number stream, use either the RandStream constructor or the RandStream.create factory method. To create multiple independent random number streams, use RandStream.create.

stream = RandStream.getDefaultStream returns the default random number stream, that is, the one currently used by the rand, randi, and randn functions.

prevstream = RandStream.setDefaultStream(stream) returns the current default stream, and designates the random number stream stream as the new default to be used by the rand, randi, and randn functions.

A random number stream s has properties that control its behavior. Access or assign to a property using p= s.Property or s.Property = p. The following table lists defined properties:

RandStream

Properties

Property	Description
Туре	(Read-only) Generator algorithm used by the stream. The list of possible generators is given by RandStream.list.
Seed	(Read-only) Seed value used to create the stream.
NumStreams	(Read-only) Number of streams in the group in which the current stream was created.
StreamIndex	(Read-only) Index of the current stream from among the group of streams with which it was created.
State	Internal state of the generator. You should not depend on the format of this property. The value you assign to S.State must be a value read from S.State previously. Use reset to return a stream to a predictable state without having previously read from the State property.
Substream	Index of the substream to which the stream is currently set. The default is 1. Multiple substreams are not supported by all generator types; the multiplicative lagged Fibonacci generator (mlfg6331_64) and combined multiple recursive generator (mrg32k3a) support multiple streams.

Property	Description
RandnAlg	Algorithm used by randn(s,) to generate normal pseudorandom values. Possible values are 'Ziggurat', 'Polar', or 'Inversion'.
Antithetic	Logical value indicating whether S generates antithetic pseudorandom values. For uniform values, these are the usual values subtracted from 1. The default is false.
FullPrecision	Logical value indicating whether S generates values using its full precision. Some generators can create pseudorandom values faster, but with fewer random bits, if FullPrecision is false. The default is true.

Methods

Method	Description
RandStream	Create a random number stream
RandStream.create	Create multiple independent random number streams
get	Get the properties of a random stream object
list	List available random number generator algorithms
set	Set random stream property

Method	Description
RandStream.getDefaultStream	Get the default random number stream
RandStream.setDefaultStream	Set the default random number stream
reset	Reset a stream to its initial internal state
rand	Pseudorandom numbers from a uniform distribution
randn	Pseudorandom numbers from a standard normal distribution
randi	Pseudorandom integers from a uniform discrete distribution
randperm	Random permutation of a set of values

See Also rand, randn, randi, rand (RandStream), randn (RandStream), randi (RandStream)

Purpose	Random number stream
Class	@RandStream
Syntax	s = RandStream('gentype') s = RandStream('gentype','param1',val1,'param2',val2)
Description	<pre>s = RandStream('gentype') creates a random number stream that uses the uniform pseudorandom number generator algorithm specified by gentype. The syntax s = RandStream('gentype','param1',val1,'param2',val2) allows you to specify optional parameter name/value pairs to control creation of the stream. Options for gentype are given by RandStream.list.</pre>

Parameters are for RandStream are:

Parameter	Description
Seed	Nonnegative scalar integer with which to initialize all streams. Default is 0. Seed must be an integer less than 2^{32} .
RandnAlg	Algorithm used by randn(s,) to generate normal pseudorandom values. Possible values are 'Ziggurat', 'Polar', or 'Inversion'.

Examples

Construct a random stream object using the combined multiple recursive generator and generate 5 uniformly distributed values from that stream.

```
stream = RandStream('mrg32k3a');
rand(stream,1,5)
```

Construct a random stream object using the multiplicative lagged Fibonacci generator and generate 5 normally distributed values using the polar algorithm.

stream = RandStream('mlfg6331_64', 'RandnAlg', 'Polar');
randn(stream,1,5)

See Also @RandStream, rand (RandStream), randn (RandStream), randi (RandStream), getDefaultStream (RandStream)

Purpose	Rank of matrix		
Syntax	k = rank(A) k = rank(A,tol)		
Description	The rank function provides an estimate of the number of linearly independent rows or columns of a full matrix.		
	<pre>k = rank(A) returns the number of singular values of A that are larger than the default tolerance, max(size(A))*eps(norm(A)).</pre>		
	k = rank(A,tol) returns the number of singular values of A that are larger than tol.		
Remark	Use sprank to determine the structural rank of a sparse matrix.		
Algorithm	There are a number of ways to compute the rank of a matrix. MATLA software uses the method based on the singular value decomposition, or SVD. The SVD algorithm is the most time consuming, but also the most reliable.		
	The rank algorithm is		
	<pre>s = svd(A); tol = max(size(A))*eps(max(s)); r = sum(s > tol);</pre>		
See Also	sprank		
References	 [1] Anderson, E., Z. Bai, C. Bischof, S. Blackford, J. Demmel, J. Dongarra, J. Du Croz, A. Greenbaum, S. Hammarling, A. McKenney, and D. Sorensen, <i>LAPACK User's Guide</i> (http://www.netlib.org/lapack/lug/lapack_lug.html), Third Edition, SIAM, Philadelphia, 1999. 		

rat, rats

Purpose	Rational fraction approximation		
Syntax	<pre>[N,D] = rat(X) [N,D] = rat(X,tol) rat(X) S = rats(X,strlen) S = rats(X)</pre>		
Description	Even though all floating-point numbers are rational numbers, it is sometimes desirable to approximate them by simple rational numbers, which are fractions whose numerator and denominator are small integers. The rat function attempts to do this. Rational approximations are generated by truncating continued fraction expansions. The rats function calls rat, and returns strings.		
	[N,D] = rat(X) returns arrays N and D so that N./D approximates X to within the default tolerance, $1.e-6*norm(X(:),1)$.		
	[N,D] = rat(X,tol) returns N./D approximating X to within tol.		
	rat(X), with no output arguments, simply displays the continued fraction.		
	S = rats(X, strlen) returns a string containing simple rational approximations to the elements of X. Asterisks are used for elements that cannot be printed in the allotted space, but are not negligible compared to the other elements in X. strlen is the length of each string element returned by the rats function. The default is strlen = 13, which allows 6 elements in 78 spaces.		
	S = rats(X) returns the same results as those printed by MATLAB with format rat.		
Examples	Ordinarily, the statement		
	s = 1 - 1/2 + 1/3 - 1/4 + 1/5 - 1/6 + 1/7		
	produces		
	s =		

0.7595 However, with format rat or with rats(s) the printed result is

s =

319/420

This is a simple rational number. Its denominator is 420, the least common multiple of the denominators of the terms involved in the original expression. Even though the quantity **s** is stored internally as a binary floating-point number, the desired rational form can be reconstructed.

To see how the rational approximation is generated, the statement rat(s) produces

1 + 1/(-4 + 1/(-6 + 1/(-3 + 1/(-5))))

And the statement

[n,d] = rat(s)

produces

n = 319, d = 420

The mathematical quantity π is certainly not a rational number, but the MATLAB quantity pi that approximates it is a rational number. pi is the ratio of a large integer and 2^{52} :

14148475504056880/4503599627370496

However, this is not a simple rational number. The value printed for pi with format rat, or with rats(pi), is

355/113

This approximation was known in Euclid's time. Its decimal representation is

3.14159292035398

and so it agrees with pi to seven significant figures. The statement

rat(pi)

produces

3 + 1/(7 + 1/(16))

This shows how the 355/113 was obtained. The less accurate, but more familiar approximation 22/7 is obtained from the first two terms of this continued fraction.

Algorithm

The rat(X) function approximates each element of X by a continued fraction of the form

$$\frac{n}{d} = d_1 + \frac{1}{d_2 + \frac{1}{\left(d_3 + \dots + \frac{1}{d_k}\right)}}$$

The ds are obtained by repeatedly picking off the integer part and then taking the reciprocal of the fractional part. The accuracy of the approximation increases exponentially with the number of terms and is worst when X = sqrt(2). For x = sqrt(2), the error with k terms is about 2.68*(.173)^k, so each additional term increases the accuracy by less than one decimal digit. It takes 21 terms to get full floating-point accuracy.

See Also format

rbbox

Purpose	Create rubberband box for area selection		
Syntax	rbbox rbbox(initialRect) rbbox(initialRect,fixedPoint) rbbox(initialRect,fixedPoint,stepSize) finalRect = rbbox()		
Description	rbbox initializes and tracks a rubberband box in the current figure. It sets the initial rectangular size of the box to 0, anchors the box at the figure's CurrentPoint, and begins tracking from this point.		
	<pre>rbbox(initialRect) specifies the initial location and size of the rubberband box as [x y width height], where x and y define the lower left corner, and width and height define the size. initialRect is in the units specified by the current figure's Units property, and measured from the lower left corner of the figure window. The corner of the box closest to the pointer position follows the pointer until rbbox receives a button-up event.</pre>		
	rbbox(initialRect,fixedPoint) specifies the corner of the box that remains fixed. All arguments are in the units specified by the current figure's Units property, and measured from the lower left corner of the figure window. fixedPoint is a two-element vector, [x y]. The tracking point is the corner diametrically opposite the anchored corner defined by fixedPoint.		
	<pre>rbbox(initialRect,fixedPoint,stepSize) specifies how frequently the rubberband box is updated. When the tracking point exceeds stepSize figure units, rbbox redraws the rubberband box. The default stepsize is 1.</pre>		
	finalRect = $rbbox()$ returns a four-element vector, [x y width height], where x and y are the x and y components of the lower left corner of the box, and width and height are the dimensions of the box.		
Remarks	rbbox is useful for defining and resizing a rectangular region:		

	 For box definition, initialRect is [x y 0 0], where (x,y) is the figure's CurrentPoint. 		
	• For box resizing, initialRect defines the rectangular region that you resize (e.g., a legend). fixedPoint is the corner diametrically opposite the tracking point.		
	rbbox returns immediately if a button is not currently pressed. Therefore, you use rbbox with waitforbuttonpress so that the mouse button is down when rbbox is called. rbbox returns when you release the mouse button.		
Examples	Assuming the current view is view(2), use the current axes' CurrentPoint property to determine the extent of the rectangle in dataspace units:		
	k = waitforbuttonpress;		
	<pre>point1 = get(gca, 'CurrentPoint');</pre>	% button down detected	
	finalRect = rbbox;	% return figure units	
	<pre>point2 = get(gca, 'CurrentPoint');</pre>	% button up detected	
	<pre>point1 = point1(1,1:2);</pre>	% extract x and y	
	point2 = point2(1,1:2);	2	
	<pre>p1 = min(point1,point2);</pre>	% calculate locations	
	offset = abs(point1-point2);		
	x = [p1(1) p1(1)+offset(1) p1(1)+offset(1) p1(1) p1(1)];		
	y = [p1(2) p1(2) p1(2)+offset(2) p1(2)+offset(2) p1(2)]; hold on		
	axis manual		
	<pre>plot(x,y)</pre>	% redraw in dataspace units	
See Also	axis, dragrect, waitforbuttonpress		
	"View Control" on page 1-109 for related functions		

Purpose	Matrix reciprocal condition number estimate		
Syntax	c = rcond(A)		
Description	c = rcond(A) returns an estimate for the reciprocal of the condition of A in 1-norm using the LAPACK condition estimator. If A is well conditioned, $rcond(A)$ is near 1.0. If A is badly conditioned, $rcond(A)$ is near 0.0. Compared to cond, $rcond$ is a more efficient, but less reliable, method of estimating the condition of a matrix.		
Algorithm	For full matrices A, rcond uses the LAPACK routines listed in the following table to compute the estimate of the reciprocal condition number.		
		Real	Complex
	A double	DLANGE, DGETRF, DGECON	ZLANGE, ZGETRF, ZGECON

	Real	Complex
A double	DLANGE, DGETRF, DGECON	ZLANGE, ZGETRF, ZGECON
A single	SLANGE, SGETRF, SGECON	CLANGE, CGETRF, CGECON

See Also cond, condest, norm, normest, rank, svd

References [1] Anderson, E., Z. Bai, C. Bischof, S. Blackford, J. Demmel, J. Dongarra, J. Du Croz, A. Greenbaum, S. Hammarling, A. McKenney, and D. Sorensen, LAPACK User's Guide (http://www.netlib.org/lapack/lug/lapack_lug.html), Third Edition, SIAM, Philadelphia, 1999.

Purpose	Read video frame data from multimedia reader object		
Syntax	<pre>video = read(obj) video = read(obj, index)</pre>		
Description	video = read(obj) reads in all video frames from the file associated with obj .		
	<pre>video = read(obj, index) reads only the specified frames. index can be a single number or a two-element array representing an index range of the video stream.</pre>		
Input Arguments	obj Name of multimedia object created with mmreader. index		
	Frames to read, where the first frame number is 1. Use Inf to represent the last frame of the file.		
	For example:		
	<pre>video = read(obj, 1); % first frame only video = read(obj, [1 10]); % first 10 frames video = read(obj, Inf); % last frame only video = read(obj, [50 Inf]); % frame 50 thru end</pre>		
	MATLAB cannot determine the number of frames in a variable frame rate file until you read the last frame. If the requested <i>index</i> extends beyond the end of the file, read returns either a warning or an error. For more information, see "Reading Variable Frame Rate Video" in the MATLAB Data Import and Export documentation.		

Default: [1 Inf]

Output Arguments	video Array of uint8 data representing RGB24 video frames. The dimensions are H-by-W-by-B-by-F, where:		
	Н	Image frame height.	
	W	Image frame width.	
	В	Number of bands in the image (for example, 3 for RGB).	
	F	Number of frames read.	
Example	Read and play back the movie file xylophone.mpg:		
	xyloObj = mmr	<pre>reader('xylophone.mpg');</pre>	
	<pre>nFrames = xyloObj.NumberOfFrames; vidHeight = xyloObj.Height; vidWidth = xyloObj.Width; % Preallocate movie structure. mov(1:nFrames) = struct('cdata', zeros(vidHeight, vidWidth, 3, 'uint8'), 'colormap', []);</pre>		
	% Read one frame at a time. for k = 1 : nFrames mov(k).cdata = read(xyloObj, k); end		
	hf = figure;	re based on the video's width and height. tion', [150 150 vidWidth vidHeight])	
	-	the movie once at the video's frame rate. 7, 1, xyloObj.FrameRate);	

See Also movie | mmreader

How To • "Reading Video Files"

Tiff.read

Purpose	Read entire image				
Syntax	imageData = tiffobj.read() [Y,Cb,Cr] = tiffobj.read()				
Description	<pre>imageData = tiffobj.read() reads the image data from the current image file directory (IFD) in the TIFF file associated with the Tiff object, tiffobj.</pre>				
	[Y,Cb,Cr] = tiffobj.read()reads the YCbCr component data from the current directory in the TIFF file. Depending upon the values of the YCbCrSubSampling tag, the size of the Cb and Cr channels might differ from the Y channel.				
Examples	<pre>Open a Tiff object and read data from the TIFF file: t = Tiff('mytif.tif', 'r'); imageData = t.read();</pre>				
See Also	Tiff.write				
Tutorials	"Exporting Image Data and Metadata to TIFF Files""Reading Image Data and Metadata from TIFF Files"				

Purpose	Read data asynchronously from device
Syntax	readasync(obj) readasync(obj,size)
Description	<pre>readasync(obj) initiates an asynchronous read operation on the serial port object, obj.</pre>
	readasync(obj,size) asynchronously reads, at most, the number of bytes given by size. If size is greater than the difference between the InputBufferSize property value and the BytesAvailable property value, an error is returned.
Remarks	Before you can read data, you must connect obj to the device with the fopen function. A connected serial port object has a Status property value of open. An error is returned if you attempt to perform a read operation while obj is not connected to the device.
	You should use readasync only when you configure the ReadAsyncMode property to manual. readasync is ignored if used when ReadAsyncMode is continuous.
	The TransferStatus property indicates if an asynchronous read or write operation is in progress. You can write data while an asynchronous read is in progress because serial ports have separate read and write pins. You can stop asynchronous read and write operations with the stopasync function.
	You can monitor the amount of data stored in the input buffer with the BytesAvailable property. Additionally, you can use the BytesAvailableFcn property to execute a callback function when the terminator or the specified amount of data is read.
	Rules for Completing an Asynchronous Read Operation
	An asynchronous read operation with readasync completes when one of these conditions is met:

• The terminator specified by the Terminator property is read.

readasync

- The time specified by the Timeout property passes.
- The specified number of bytes is read.
- The input buffer is filled (if size is not specified).

Because readasync checks for the terminator, this function can be slow. To increase speed, you might want to configure ReadAsyncMode to continuous and continuously return data to the input buffer as soon as it is available from the device.

Example

This example creates the serial port object **s** on a Windows platform. It connects **s** to a Tektronix TDS 210 oscilloscope, configures **s** to read data asynchronously only if **readasync** is issued, and configures the instrument to return the peak-to-peak value of the signal on channel 1.

```
s = serial('COM1');
fopen(s)
s.ReadAsyncMode = 'manual';
fprintf(s,'Measurement:Meas1:Source CH1')
fprintf(s,'Measurement:Meas1:Type Pk2Pk')
fprintf(s,'Measurement:Meas1:Value?')
```

Begin reading data asynchronously from the instrument using readasync. When the read operation is complete, return the data to the MATLAB workspace using fscanf.

See Also Functions

fopen, stopasync

Properties

BytesAvailable, BytesAvailableFcn, ReadAsyncMode, Status, TransferStatus

Purpose	Read data from specified strip					
Syntax	stripData = tiffobj.readEncodedStrip(stripNumber) [Y,Cb,Cr] = tiffobj.readEncodedStrip(stripNumber)					
Description	<pre>stripData = tiffobj.readEncodedStrip(stripNumber) reads data from the strip specified by stripNumber. Strip numbers are one-based numbers.</pre>					
	<pre>[Y,Cb,Cr] = tiffobj.readEncodedStrip(stripNumber) reads YCbCr component data from the specified strip. The size of the chrominance components Cb and Cr might differ from the size of the luminance component Y depending on the value of the YCbCrSubSampling tag.</pre>					
	readEncodeStrip clips the last strip, if the strip extends past the ImageLength boundary.					
Examples	Open a Tiff object and read a strip of data. Replace myfile.tif with the name of a TIFF file on your MATLAB path.					
	<pre>t = Tiff('myfile.tif', 'r'); % % Check if image is tiled or stipped. if ~t.isTiled() data = t.readEncodedStrip(1); end</pre>					
References	This method corresponds to the TIFFReadEncodedStrip function in the LibTIFF C API. To use this method, you must be familiar with LibTIFF version 3.7.1, as well as the TIFF specification and technical notes. View this documentation at LibTIFF - TIFF Library and Utilities.					
See Also	Tiff.readEncodedTile Tiff.isTiled					
Tutorials	"Exporting Image Data and Metadata to TIFF Files""Reading Image Data and Metadata from TIFF Files"					

Purpose	Read data from specified tile				
Syntax	tileData = tiffobj.readEncodedTile(tileNumber) [Y,Cb,Cr] = tiffobj.readEncodedTile(tileNumber)				
Description	<pre>tileData = tiffobj.readEncodedTile(tileNumber) reads data from the tile specified by tileNumber. Tile numbers are one-based numbers. [Y,Cb,Cr] = tiffobj.readEncodedTile(tileNumber) reads YCbCr component data from the specified tile. The size of the chrominance components Cb and Cr might differ from the size of the luminance component Y, depending on the value of the YCbCrSubSampling tag. readEncodedTile clips tiles on the last row or right-most column of</pre>				
_	an image if the tile extends past the ImageLength and ImageLength boundaries.				
Examples	<pre>Open a Tiff object and read a tile of data. Replace myfile.tif with the name of a TIFF file on your MATLAB path. t = Tiff('myfile.tif', 'r'); % % Check if image is tiled or stipped. if t.isTiled() data = t.readEncodedTile(1); end</pre>				
	References				
	This method corresponds to the TIFFReadEncodedTile function in the LibTIFF C API. To use this method, you must be familiar with LibTIFF version 3.7.1, as well as the TIFF specification and technical notes. View this documentation at LibTIFF - TIFF Library and Utilities.				
See Also	Tiff.readEncodedStrip Tiff.isTiled				
Tutorials	"Exporting Image Data and Metadata to TIFF Files"				

• "Reading Image Data and Metadata from TIFF Files"

Purpose	Real part of complex number		
Syntax	X = real(Z)		
Description	X = real(Z) returns the real part of the elements of the complex array Z.		
Examples	real(2+3*i) is 2.		
See Also	abs, angle, conj, i, j, imag		

reallog

Purpose	Natural logarithm for nonnegative real arrays				
Syntax	Y = reallog(X)				
Description	Y = reallog(X) returns the natural logarithm of each element in array X. Array X must contain only nonnegative real numbers. The size of Y is the same as the size of X.				
Examples	M = magic(4)				
	M = 16 2 3 13 5 11 10 8 9 7 6 12 4 14 15 1 reallog(M)				
	ans = 2.7726 0.6931 1.0986 2.5649 1.6094 2.3979 2.3026 2.0794 2.1972 1.9459 1.7918 2.4849 1.3863 2.6391 2.7081 0				
See Also	log, realpow, realsqrt				

realmax

Purpose	Largest positive floating-point number					
Syntax	n = realmax					
Description	n = realmax returns the largest floating-point number representable on your computer. Anything larger overflows.					
	realmax('double') is the same as realmax with no arguments.					
	<pre>realmax('single') is the largest single precision floating point number representable on your computer. Anything larger overflows to single(Inf).</pre>					
Examples	realmax is one bit less than 2^{1024} or about 1.7977e+308.					
Algorithm	The realmax function is equivalent to pow2(2-eps,maxexp), where maxexp is the largest possible floating-point exponent.					
	Execute type realmax to see maxexp for various computers.					
See Also	eps, realmin, intmax					

realmin

Purpose	Smallest positive normalized floating-point number				
Syntax	n = realmin				
Description	n = realmin returns the smallest positive normalized floating-point number on your computer. Anything smaller underflows or is an IEEE "denormal."				
	REALMIN('double') is the same as REALMIN with no arguments.				
	REALMIN('single') is the smallest positive normalized single precision floating point number on your computer.				
Examples	realmin is 2^(-1022) or about 2.2251e-308.				
Algorithm	The realmin function is equivalent to pow2(1,minexp) where minexp is the smallest possible floating-point exponent.				
	Execute type realmin to see minexp for various computers.				
See Also	eps, realmax, intmin				

Purpose	Array power for real-only output				
Syntax	Z = realpow(X,Y)				
Description	Z = realpow(X,Y) raises each element of array X to the power of its corresponding element in array Y. Arrays X and Y must be the same size. The range of realpow is the set of all real numbers, i.e., all elements of the output array Z must be real.				
Examples	X = -2*ones(3,3)				
	X = -2 -2 -2 -2 -2 -2 -2 -2 -2 -2 -2 Y = pascal(3) ans = 1 1 1 1 1 2 3 1 3 6				
	<pre>realpow(X,Y)</pre>				
	ans = -2 -2 -2				
	-2 4 -8 -2 -8 64				
_					

See Also

reallog, realsqrt, .^ (array power operator)

realsqrt

Purpose	Square root for nonnegative real arrays						
Syntax	Y = realsqrt(X)						
Description	Y = realsqrt(X) returns the square root of each element of array X. Array X must contain only nonnegative real numbers. The size of Y is the same as the size of X.						
Examples	M = magic(4)						
	М =						
		2	3	13			
	5	11	10	8			
	9	7	6	12			
	4	14	15	1			
	realsqrt(M)						
	ans =						
	4.0000		1.4142	1.7	7321	3.6056	
	2.2361		3.3166	3.	1623	2.8284	
	3.0000		2.6458	2.4	4495	3.4641	
	2.0000		3.7417	3.8	3730	1.0000	
See Also	reallog, realp	oow,	, sqrt, sq	rtm			

Purpose	Record data and event information to file
Syntax	record(obj) record(obj,' <i>switch</i> ')
Description	<pre>record(obj) toggles the recording state for the serial port object, obj. record(obj,'switch') initiates or terminates recording for obj.</pre>
	switch can be on or off. If switch is on, recording is initiated. If switch is off, recording is terminated.
Remarks	Before you can record information to disk, obj must be connected to the device with the fopen function. A connected serial port object has a Status property value of open. An error is returned if you attempt to record information while obj is not connected to the device. Each serial port object must record information to a separate file. Recording is automatically terminated when obj is disconnected from the device with fclose.
	The RecordName and RecordMode properties are read-only while obj is recording, and must be configured before using record.
	For a detailed description of the record file format and the properties associated with recording data and event information to a file, refer to Debugging: Recording Information to Disk.
Example	This example creates the serial port object s on a Windows platform. It connects s to the device, configures s to record information to a file, writes and reads text data, and then disconnects s from the device.
	<pre>s = serial('COM1'); fopen(s) s.RecordDetail = 'verbose'; s.RecordName = 'MySerialFile.txt'; record(s,'on') fprintf(s,'*IDN?') out = fscanf(s); record(s,'off')</pre>

fclose(s)

See Also Functions

fclose, fopen

Properties

RecordDetail, RecordMode, RecordName, RecordStatus, Status


Purpose	Record audio to audiorecorder object				
Syntax	record(<i>recorderObj</i>) record(<i>recorderObj, length</i>)				
Description	record(<i>recorderObj</i>) records audio from an input device, such as a microphone connected to your system. <i>recorderObj</i> is an audiorecorder object that defines the sample rate, bit depth, and other properties of the recording.				
	<pre>record(recorderObj, length) records for the number of seconds specified by length.</pre>				
Example	<pre>Record 5 seconds of your speech with a microphone: myVoice = audiorecorder; % Define callbacks to show when % recording starts and completes. myVoice.StartFcn = 'disp(''Start speaking.'')'; myVoice.StopFcn = 'disp(''End of recording.'')'; record(myVoice, 5); To listen to the recording, call the play method: play(myVoice);</pre>				
See Also	audiorecorder getaudiodata recordblocking				
How To	 "Recording Audio" "Recording or Playing Audio within a Function"				

Purpose	Record audio to audiorecorder object, holding control until recording completes
Syntax	<pre>recordblocking(recorderObj, length)</pre>
Description	recordblocking(<i>recorderObj</i> , <i>length</i>) records audio from an input device, such as a microphone connected to your system, for the number of seconds specified by <i>length</i> . The recordblocking method does not return control until recording completes. <i>recorderObj</i> is an audiorecorder object that defines the sample rate, bit depth, and other properties of the recording.
Examples	<pre>Record 5 seconds of your speech with a microphone, and play it back: myVoice = audiorecorder; disp('Start speaking.'); recordblocking(myVoice, 5); disp('End of recording. Playing back'); play(myVoice);</pre>
See Also	audiorecorder getaudiodata record
How To	"Recording Audio"


Purpose	Create 2-D rectangle object
Syntax	<pre>rectangle rectangle('Position',[x,y,w,h]) rectangle('Curvature',[x,y]) rectangle('PropertyName',propertyvalue,) h = rectangle()</pre>
Properties	For a list of properties, see Rectangle Properties.
Description	rectangle draws a rectangle with Position [0,0,1,1] and Curvature [0,0] (i.e., no curvature).
	rectangle('Position',[x,y,w,h]) draws the rectangle from the point x,y and having a width of w and a height of h. Specify values in axes data units.
	Note that, to display a rectangle in the specified proportions, you need to set the axes data aspect ratio so that one unit is of equal length along both the x and y axes. You can do this with the command axis equal or daspect([1,1,1]).
	rectangle('Curvature', $[x,y]$) specifies the curvature of the rectangle sides, enabling it to vary from a rectangle to an ellipse. The horizontal curvature x is the fraction of width of the rectangle that is curved along the top and bottom edges. The vertical curvature y is the fraction of the height of the rectangle that is curved along the left and right edges.
	The values of x and y can range from 0 (no curvature) to 1 (maximum curvature). A value of [0,0] creates a rectangle with square sides. A value of [1,1] creates an ellipse. If you specify only one value for Curvature, then the same length (in axes data units) is curved along both horizontal and vertical sides. The amount of curvature is determined by the shorter dimension.
	rectangle('PropertyName',propertyvalue,) draws the rectangle using the values for the property name/property value pairs specified and default values for all other properties. For a description of the properties, see Rectangle Properties.

	h = rectangle() returns the handle of the rectangle object created.		
Remarks	Rectangle objects are 2-D and can be drawn in an axes only if the view is [0 90] (i.e., view(2)). Rectangles are children of axes and are defined in coordinates of the axes data.		
Examples	This example sets the data aspect ratio to [1,1,1] so that the rectangle is displayed in the specified proportions (daspect). Note that the horizontal and vertical curvature can be different. Also, note the effects of using a single value for Curvature.		
	rectangle('Position',[0.59,0.35,3.75,1.37], 'Curvature',[0.8,0.4], 'LineWidth',2,'LineStyle','') daspect([1,1,1])		
	2 1.8 1.6 1.4 1.2 1 0.8 0.6 0.4 0.2		
	0.5 1 1.5 2 2.5 3 3.5 4 4.5		

Specifying a single value of [0.4] for Curvature produces



This example creates an ellipse and colors the face red.



Setting Default Properties

You can set default rectangle properties on the axes, figure, and root object levels:

set(0, 'DefaultRectangleProperty', PropertyValue...)
set(gcf, 'DefaultRectangleProperty', PropertyValue...)
set(gca, 'DefaultRectangleProperty', PropertyValue...)

where *Property* is the name of the rectangle property whose default value you want to set and **PropertyValue** is the value you are specifying. Use set and get to access the surface properties.

See Also line, patch

Rectangle Properties for property descriptions

"Object Creation" on page 1-104 for related functions

See the ${\tt annotation}$ function for information about the rectangle annotation object.

Rectangle Properties

Purpose	Define rectangle properties	
Creating Rectangle Objects	Use rectangle to create rectangle objects.	
Modifying Properties	 You can set and query graphics object properties in two ways: "The Property Editor" is an interactive tool that enables you to see and change object property values. The set and get commands enable you to set and query the values of properties. To change the default values of properties, see "Setting Default Property Values". See "Core Graphics Objects" for general information about this type of object. 	
Rectangle Property Descriptions	 This section lists property names along with the type of values each accepts. Curly braces {} enclose default values. Annotation hg.Annotation object Read Only Control the display of rectangle objects in legends. The Annotation property enables you to specify whether this rectangle object is represented in a figure legend. Querying the Annotation property returns the handle of an hg.Annotation object. The hg.Annotation object has a property called LegendInformation, which contains an hg.LegendEntry object. 	

Once you have obtained the hg.LegendEntry object, you can set its IconDisplayStyle property to control whether the rectangle object is displayed in a figure legend:

IconDisplayStyle Value	Purpose
on	Represent this rectangle object in a legend (default)
off	Do not include this rectangle object in a legend
children	Same as on because rectangle objects do not have children

Setting the IconDisplayStyle property

These commands set the IconDisplayStyle of a graphics object with handle hobj to off:

```
hAnnotation = get(hobj, 'Annotation');
hLegendEntry = get(hAnnotation', 'LegendInformation');
set(hLegendEntry, 'IconDisplayStyle', 'off')
```

Using the IconDisplayStyle property

See "Controlling Legends" for more information and examples.

BeingDeleted

on | {off} read only

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. The MATLAB software sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists. For example, an object's delete function might call other functions that act on a number of different objects. These functions may not need to perform actions on objects that are going to be deleted, and therefore, can check the object's BeingDeleted property before acting.

```
BusyAction
```

cancel | {queue}

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callback routines. If there is a callback routine executing, callback routines invoked subsequently always attempt to interrupt it. If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are

- cancel Discard the event that attempted to execute a second callback routine.
- queue Queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Button press callback function. A callback function that executes whenever you press a mouse button while the pointer is over the rectangle object.

See the figure's SelectionType property to determine if modifier keys were also pressed.

Set this property to a function handle that references the callback. The function must define at least two input arguments (handle of object associated with the button down event and an event structure, which is empty for this property)

```
function button down(src,evnt)
% src - the object that is the source of the event
% evnt - empty for this property
   sel typ = get(gcbf, 'SelectionType')
   switch sel typ
      case 'normal'
         disp('User clicked left-mouse button')
         set(src,'Selected','on')
      case 'extend'
         disp('User did a shift-click')
         set(src,'Selected','on')
      case 'alt'
         disp('User did a control-click')
         set(src,'Selected','on')
         set(src,'SelectionHighlight','off')
   end
end
```

Suppose h is the handle of a rectangle object and that the button_down function is on your MATLAB path. The following statement assigns the function above to the ButtonDownFcn:

set(h, 'ButtonDownFcn',@button_down)

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

Children

vector of handles

The empty matrix; rectangle objects have no children.

Clipping

{on} | off

Clipping mode. MATLAB clips rectangles to the axes plot box by default. If you set Clipping to off, rectangles are displayed outside the axes plot box. This can occur if you create a rectangle, set hold to on, freeze axis scaling (axis set to manual), and then create a larger rectangle.

CreateFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Callback function executed during object creation. This property defines a callback function that executes when MATLAB creates a rectangle object. You must define this property as a default value for rectangles or in a call to the rectangle function to create a new rectangle object. For example, the statement

set(0, 'DefaultRectangleCreateFcn',@rect_create)

defines a default value for the rectangle CreateFcn property on the root level that sets the axes DataAspectRatio whenever you create a rectangle object. The callback function must be on your MATLAB path when you execute the above statement.

```
function rect_create(src,evnt)
% src - the object that is the source of the event
% evnt - empty for this property
axh = get(src,'Parent');
set(axh,'DataAspectRatio',[1,1,1]))
end
```

MATLAB executes this function after setting all rectangle properties. Setting this property on an existing rectangle object has no effect. The function must define at least two input arguments (handle of object created and an event structure, which is empty for this property).

The handle of the object whose CreateFcn is being executed is passed by MATLAB as the first argument to the callback function

and is also accessible through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

Curvature

one- or two-element vector [x,y]

Amount of horizontal and vertical curvature. This property specifies the curvature of the rectangle sides, which enables the shape of the rectangle to vary from rectangular to ellipsoidal. The horizontal curvature x is the fraction of width of the rectangle that is curved along the top and bottom edges. The vertical curvature y is the fraction of the height of the rectangle that is curved along the left and right edges.

The values of x and y can range from 0 (no curvature) to 1 (maximum curvature). A value of [0,0] creates a rectangle with square sides. A value of [1,1] creates an ellipse. If you specify only one value for Curvature, then the same length (in axes data units) is curved along both horizontal and vertical sides. The amount of curvature is determined by the shorter dimension.

DeleteFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Delete rectangle callback function. A callback function that executes when you delete the rectangle object (for example, when you issue a delete command or clear the axes cla or figure clf). For example, the following function displays object property data before the object is deleted.

```
function delete_fcn(src,evnt)
% src - the object that is the source of the event
% evnt - empty for this property
    obj_tp = get(src,'Type');
```

```
disp([obj_tp, ' object deleted'])
disp('Its user data is:')
disp(get(src,'UserData'))
end
```

MATLAB executes the function before deleting the object's properties so these values are available to the callback function. The function must define at least two input arguments (handle of object being deleted and an event structure, which is empty for this property)

The handle of the object whose DeleteFcn is being executed is passed by MATLAB as the first argument to the callback function and is also accessible through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DisplayName

string (default is empty string)

String used by legend for this rectangle object. The legend function uses the string defined by the DisplayName property to label this rectangle object in the legend.

- If you specify string arguments with the legend function, DisplayName is set to this rectangle object's corresponding string and that string is used for the legend.
- If DisplayName is empty, legend creates a string of the form, ['data' n], where n is the number assigned to the object based on its location in the list of legend entries. However, legend does not set DisplayName to this string.
- If you edit the string directly in an existing legend, DisplayName is set to the edited string.

- If you specify a string for the DisplayName property and create the legend using the figure toolbar, then MATLAB uses the string defined by DisplayName.
- To add programmatically a legend that uses the DisplayName string, call legend with the toggle or show option.

See "Controlling Legends" for more examples.

EdgeColor

{ColorSpec} | none

Color of the rectangle edges. This property specifies the color of the rectangle edges as a color or specifies that no edges be drawn.

EraseMode

{normal} | none | xor | background

Erase mode. This property controls the technique MATLAB uses to draw and erase rectangle objects. Alternative erase modes are useful for creating animated sequences, where control of the way individual objects are redrawn is necessary to improve performance and obtain the desired effect.

- normal (the default) Redraw the affected region of the display, performing the three-dimensional analysis necessary to ensure that all objects are rendered correctly. This mode produces the most accurate picture, but is the slowest. The other modes are faster, but do not perform a complete redraw and are therefore less accurate.
- none Do not erase the rectangle when it is moved or destroyed. While the object is still visible on the screen after erasing with EraseMode none, you cannot print it because MATLAB stores no information about its former location.
- xor Draw and erase the rectangle by performing an exclusive OR (XOR) with the color of the screen beneath it. This mode does not damage the color of the objects beneath the rectangle.

However, the rectangle's color depends on the color of whatever is beneath it on the display.

• background — Erase the rectangle by drawing it in the axes background Color, or the figure background Color if the axes Color is set to none. This damages objects that are behind the erased rectangle, but rectangles are always properly colored.

Printing with Nonnormal Erase Modes

MATLAB always prints figures as if the EraseMode of all objects is normal. This means graphics objects created with EraseMode set to none, xor, or background can look different on screen than on paper. On screen, MATLAB can mathematically combine layers of colors (for example, performing an XOR of a pixel color with that of the pixel behind it) and ignore three-dimensional sorting to obtain greater rendering speed. However, these techniques are not applied to the printed output.

You can use the MATLAB getframe command or other screen capture application to create an image of a figure containing nonnormal mode objects.

FaceColor

ColorSpec | {none}

Color of rectangle face. This property specifies the color of the rectangle face, which is not colored by default.

HandleVisibility

{on} | callback | off

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally drawing into or deleting a figure that contains only user interface devices (such as a dialog box). Handles are always visible when HandleVisibility is on.

Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.

Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close.

When a handle's visibility is restricted using callback or off, the object's handle does not appear in its parent's Children property, figures do not appear in the root's CurrentFigure property, objects do not appear in the root's CallbackObject property or in the figure's CurrentObject property, and axes do not appear in their parent's CurrentAxes property.

You can set the Root ShowHiddenHandles property to on to make all handles visible regardless of their HandleVisibility settings (this does not affect the values of the HandleVisibility properties).

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties and pass it to any function that operates on handles.

HitTest {on} | off

> Selectable by mouse click. HitTest determines if the rectangle can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click on the rectangle. If HitTest is off, clicking the rectangle selects the object below it (which may be the axes containing it).

Interruptible

{on} | off

Callback routine interruption mode. The Interruptible property controls whether a rectangle callback routine can be interrupted by subsequently invoked callback routines. Only callback routines defined for the ButtonDownFcn are affected by the Interruptible property. MATLAB checks for events that can interrupt a callback routine only when it encounters a drawnow, figure, getframe, or pause command in the routine.

LineStyle

{-} | -- | : | -. | none

Line style of rectangle edge. This property specifies the line style of the edges. The available line styles are

Symbol	Line Style
-	Solid line (default)
	Dashed line
:	Dotted line
	Dash-dot line
none	No line

LineWidth scalar

The width of the rectangle edge line. Specify this value in points (1 point = $\frac{1}{72}$ inch). The default LineWidth is 0.5 points.

Parent

handle of axes, hggroup, or hgtransform

Parent of rectangle object. This property contains the handle of the rectangle object's parent. The parent of a rectangle object is the axes, hggroup, or hgtransform object that contains it.

See "Objects That Can Contain Other Objects" for more information on parenting graphics objects.

Position

four-element vector [x,y,width,height]

Location and size of rectangle. This property specifies the location and size of the rectangle in the data units of the axes. The point defined by x, y specifies one corner of the rectangle, and width and height define the size in units along the x-and y-axes respectively.

Selected

on | off

Is object selected? When this property is on MATLAB displays selection handles if the SelectionHighlight property is also on. You can, for example, define the ButtonDownFcn to set this property, allowing users to select the object with the mouse.

SelectionHighlight

{on} | off

Objects are highlighted when selected. When the Selected property is on, MATLAB indicates the selected state by drawing handles at each vertex. When SelectionHighlight is off, MATLAB does not draw the handles.

Тад

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when you are constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callback routines. You can define Tag as any string.

Туре

string (read only)

Class of graphics object. For rectangle objects, Type is always the string 'rectangle'.

UIContextMenu

handle of a uicontextmenu object

Associate a context menu with the rectangle. Assign this property the handle of a uicontextmenu object created in the same figure as the rectangle. Use the uicontextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click over the rectangle.

UserData

matrix

User-specified data. Any data you want to associate with the rectangle object. MATLAB does not use this data, but you can access it using the set and get commands.

Visible

{on} | off

Rectangle visibility. By default, all rectangles are visible. When set to off, the rectangle is not visible, but still exists, and you can get and set its properties.

See Also rectangle

Purpose	Rectangle intersection area
Syntax	area = rectint(A,B)
Description	area = $rectint(A,B)$ returns the area of intersection of the rectangles specified by position vectors A and B.
	If A and B each specify one rectangle, the output area is a scalar.
	A and B can also be matrices, where each row is a position vector. area is then a matrix giving the intersection of all rectangles specified by A with all the rectangles specified by B. That is, if A is n-by-4 and B is m-by-4, then area is an n-by-m matrix where area(i,j) is the intersection area of the rectangles specified by the ith row of A and the jth row of B.
	Note A position vector is a four-element vector [x,y,width,height], where the point defined by x and y specifies one corner of the rectangle, and width and height define the size in units along the x and y axes respectively.
C A1	

See Also polyarea

recycle

Purpose	Set option to move deleted files to recycle folder
Syntax	recycle stat = recycle previousStat = recycle <i>state</i> previousStat = recycle('state')
Description	recycle displays the current state, on or off, for recycling files you remove using the delete function. When the value is on, deleted files move to a different location. The location varies by platform—see "Deleting Files and Folders Using Functions". When the value is off, the delete function permanently removes the files. For details, see the Remarks section.
	<pre>stat = recycle returns the current state for recycling files to the character array stat.</pre>
	<pre>previousStat = recycle state sets the recycle option for MATLAB to the specified state, either on or off. The previousStat value is the recycle state before running the statement.</pre>
	<pre>previousStat = recycle('state') is the function form of the syntax.</pre>
Remarks	The preference for Deleting files sets the state of the recycle function at startup. When you change the preference, it changes the state of recycle. When you change the state of recycle, it does not change the preference. Use recycle to override the behavior of the preference. For example, regardless of the setting for the Deleting files preference, to remove thisfile.m permanently, run:
	recycle('off') delete('thisfile.m')
	After setting the recycle state to off, all files you delete using the delete function are deleted permanently until you do one of the following:

• Run recycle('on')


	• Restart MATLAB. Upon startup, MATLAB sets the state for recycle to match the Deleting files preference.
Examples	Start from a state where file recycling is off. Verify the current recycle state:
	recycle
	ans =
	off
	Turn file recycling on. Delete a file and move it to the recycle bin or temporary folder:
	recycle on;
	delete myfile.txt
See Also	delete, dir, ls, rmdir
	"Managing Files in MATLAB"

reducepatch


Purpose	Reduce number of patch faces
Syntax	<pre>nfv = reducepatch(p,r) nfv = reducepatch(fv,r) nfv = reducepatch(p) or nfv = reducepatch(fv) reducepatch(,'fast') reducepatch(,'verbose') nfv = reducepatch(f,v,r) [nf,nv] = reducepatch()</pre>
Description	reducepatch(p,r) reduces the number of faces of the patch identified by handle p, while attempting to preserve the overall shape of the original object. The MATLAB software interprets the reduction factor r in one of two ways depending on its value:
	• If r is less than 1, r is interpreted as a fraction of the original number of faces. For example, if you specify r as 0.2, then the number of faces is reduced to 20% of the number in the original patch.
	• If r is greater than or equal to 1, then r is the target number of faces. For example, if you specify r as 400, then the number of faces is reduced until there are 400 faces remaining.
	nfv = reducepatch(p,r) returns the reduced set of faces and vertices but does not set the Faces and Vertices properties of patch p. The struct nfv contains the faces and vertices after reduction.
	nfv = reducepatch(fv,r) performs the reduction on the faces and vertices in the struct fv.
	nfv = reducepatch(p) or $nfv = reducepatch(fv)$ uses a reduction value of 0.5.
	<pre>reducepatch(,'fast') assumes the vertices are unique and does not compute shared vertices.</pre>
	<pre>reducepatch(,'verbose') prints progress messages to the command window as the computation progresses.</pre>

	nfv = reducepatch(f,v,r) performs the reduction on the faces in f and the vertices in v.
	[nf,nv] = reducepatch() returns the faces and vertices in the arrays nf and nv.
Remarks	If the patch contains nonshared vertices, MATLAB computes shared vertices before reducing the number of faces. If the faces of the patch are not triangles, MATLAB triangulates the faces before reduction. The faces returned are always defined as triangles.
	The number of output triangles may not be exactly the number specified with the reduction factor argument (r), particularly if the faces of the original patch are not triangles.
Examples	This example illustrates the effect of reducing the number of faces to only 15% of the original value.
	<pre>[x,y,z,v] = flow; p = patch(isosurface(x,y,z,v,-3)); set(p,'facecolor','w','EdgeColor','b'); daspect([1,1,1]) view(3) figure; h = axes; p2 = copyobj(p,h); reducepatch(p2,0.15) daspect([1,1,1]) view(3)</pre>

reducepatch



2-3282




After Reduction to 15% of Original Number of Faces

See Also isosurface, isocaps, isonormals, smooth3, subvolume, reducevolume "Volume Visualization" on page 1-111 for related functions Vector Field Displayed with Cone Plots for another example

reducevolume

Purpose	Reduce number of elements in volume data set
Syntax	<pre>[nx,ny,nz,nv] = reducevolume(X,Y,Z,V,[Rx,Ry,Rz]) [nx,ny,nz,nv] = reducevolume(V,[Rx,Ry,Rz]) nv = reducevolume()</pre>
Description	$[nx,ny,nz,nv] = reducevolume(X,Y,Z,V,[Rx,Ry,Rz])$ reduces the number of elements in the volume by retaining every Rx^{th} element in the <i>x</i> direction, every Ry^{th} element in the <i>y</i> direction, and every Rz^{th} element in the <i>z</i> direction. If a scalar R is used to indicate the amount or reduction instead of a three-element vector, the MATLAB software assumes the reduction to be [R R R].
	The arrays X, Y, and Z define the coordinates for the volume V. The reduced volume is returned in nv , and the coordinates of the reduced volume are returned in nx , ny , and nz .
	<pre>[nx,ny,nz,nv] = reducevolume(V,[Rx,Ry,Rz]) assumes the arrays X, Y, and Z are defined as [X,Y,Z] = meshgrid(1:n,1:m,1:p), where [m,n,p] = size(V).</pre>
	nv = reducevolume() returns only the reduced volume.
Examples	This example uses a data set that is a collection of MRI slices of a human skull. This data is processed in a variety of ways:
	• The 4-D array is squeezed (squeeze) into three dimensions and then reduced (reducevolume) so that what remains is every fourth element in the <i>x</i> and <i>y</i> directions and every element in the <i>z</i> direction.
	• The reduced data is smoothed (smooth3).
	• The outline of the skull is an isosurface generated as a patch (p1) whose vertex normals are recalculated to improve the appearance when lighting is applied (patch, isosurface, isonormals).
	• A second patch (p2) with an interpolated face color draws the end caps (FaceColor) isocaps).
	• The view of the object is set (view, axis, daspect).

- A 100-element grayscale colormap provides coloring for the end caps (colormap).
- Adding a light to the right of the camera illuminates the object (camlight, lighting).





isosurface, isocaps, isonormals, smooth3, subvolume, reducepatch

"Volume Visualization" on page 1-111 for related functions

refresh

Purpose	Redraw current figure
Syntax	refresh refresh(h)
Description	refresh erases and redraws the current figure. refresh(h) redraws the figure identified by h.
See Also	"Figure Windows" on page 1-105 for related functions

refreshdata

Purpose	Refresh data in graph when data source is specified
Syntax	refreshdata refreshdata(figure_handle) refreshdata(object_handles) refreshdata(object_handles,' <i>workspace</i> ')
Description	refreshdata evaluates any data source properties (XDataSource, YDataSource, or ZDataSource) on all objects in graphs in the current figure. If the specified data source has changed, the MATLAB software updates the graph to reflect this change.
	Note that the variable assigned to the data source property must be in the base workspace.
	refreshdata(figure_handle) refreshes the data of the objects in the specified figure.
	refreshdata(object_handles) refreshes the data of the objects specified in object_handles or the children of those objects. Therefore, object_handles can contain figure, axes, or plot object handles.
	<pre>refreshdata(object_handles, 'workspace') enables you to specify whether the data source properties are evaluated in the base workspace or the workspace of the function in which refreshdata was called. workspace is a string that can be</pre>
	• base — Evaluate the data source properties in the base workspace.
	• caller — Evaluate the data source properties in the workspace of the function that called refreshdata.
Remarks	The Linked Plots feature (see documentation for linked) sets up data sources for graphs and synchronizes them with the workspace variables they display. When you use this feature, you do not also need to call refreshdata, as it is essentially automatically triggered every time a data source changes.

If you are not using the Linked Plots feature, you need to set the XDataSource, YDataSource, and/or ZDataSource properties of a graph in order to use refreshdata. You can do that programmatically, as shown in the examples below, or use the Property Editor, one of the plotting tools. In the Property Editor, select the graph (e.g., a lineseries object) and type in (or select from the drop-down choices) the name(s) of the workspace variable(s) from which you want the plot to refresh, in the fields labelled **X Data Source**, **Y Data Source**, and/or **Z Data Source**. The call to refreshdata causes the graph to update.

Examples Plot a sine wave, identify data sources, and then modify its YDataSource:

```
x = 0:.1:8;
y = sin(x);
h = plot(x,y)
set(h,'YDataSource','y')
set(h,'XDataSource','x')
y = sin(x.^3);
refreshdata
```

Create a surface plot, identify a ZDataSource for it, and change the data to a different size.

```
Z = peaks(5);
h = surf(Z)
set(h,'ZDataSource','Z')
pause(3)
Z = peaks(25);
refreshdata
```

See Also The [X,Y,Z]DataSource properties of plot objects.

regexp, regexpi

Purpose	Match regular expression
Syntax	<pre>regexp(parseStr, matchExpr) [startIndex, endIndex, tokIndex, matchStr, tokenStr, exprNames, splitStr] = regexp(parseStr, matchExpr) [outVal1, outVal5,] = regexp(str, expr, outSel1, outSel5,) [v1 v2] = regexp(str, expr,, options)</pre>
Description	Each of the above syntaxes applies to both regexp and regexpi. The regexp function is case sensitive in matching regular expressions to a string, and regexpi is case insensitive.
	regexp(parseStr, matchExpr) returns a row vector containing the starting index of each substring of parseStr that matches the regular expression string matchExpr. If no matches are found, regexp returns an empty array. The parseStr and matchExpr arguments can also be cell arrays of strings. See "Regular Expressions" in the MATLAB Programming Fundamentals documentation for more information.
	To specify more than one string to parse or more than one expression to match, see the guidelines listed below under "Multiple Strings or Expressions" on page 2-3298.
	[startIndex, endIndex, tokIndex, matchStr, tokenStr, exprNames, splitStr] = regexp(<i>parseStr</i> , <i>matchExpr</i>) returns up to six values, one for each output variable you specify, and in the default order (as shown in the table below).
	Note The <i>str</i> and <i>expr</i> inputs are required and must be entered as the first and second arguments, respectively. Any other input arguments (all are described below) are optional and can be entered following the two required inputs in any order.

[outVal1, outVal5, ...] = regexp(str, expr, outSel1, outSel5, ...) returns up to six values, one for each output variable you specify, and ordered according to the order of the qualifier arguments, q1, q2, etc.

Tip When using the split option, regexp always returns one more string than it does with the match option. Also, you can always put the original input string back together from the substrings obtained from both split and match. See "Example 4 — Splitting the Input String" on page 2-3300.

[v1 v2 ...] = regexp(str, expr, ..., options) calls regexp with one or more of the nondefault options listed in the following table. These options must follow str and expr in the input argument list.

Option	Description	
mode	See the section on Modes under Inputs, below.	
'once'	Return only the first match found.	
'warnings'	Display any hidden warning messages issued by MATLAB during the execution of the command. This option only enables warnings for the one command being executed. See "Example 11 — Displaying Parsing Warnings" on page 2-3305.	

Input Arguments

A string MATLAB that searches for a substring that matches the regular expression. It can be of any length and may contain any characters.

expr

str

A combination of text and operators that enable you to specify the content of the phrase you are looking for in the parse string. Any

text in the expression must be an exact match for at least part of the text in the parse string. Operators, on the other hand, are symbolic. Each operator symbol stands for a *type* of character (e.g., an uppercase letter ([A-Z]), a space character (\s), four characters of any type (. {4})).

MATLAB parses the input string from left to right, attempting to match text in the string with the first element of the regular expression. During this process, **MATLAB** skips over any text that does not match. When it finds the first match, it continues parsing the string, this time attempting to match the second piece of the expression, and so on. If characters are detected in the string that do not match the expression, then MATLAB drops the current match candidate and again starts looking for a match with the first element of the expression.

outputSelect

Qualifier	Description	Default Order
start	Row vector containing the starting index of each substring of str that matches expr.	1
end	Row vector containing the ending index of each substring of str that matches expr.	2
tokenExter	tS ell array containing the starting and ending indices of each substring of str that matches a token in expr. (This is a double array when used with 'once'.)	3
match	Cell array containing the text of each substring of str that matches expr. (This is a string when used with 'once'.)	4

One to seven keywords with which you can select which output values regexp is to return and in what order.

Qualifier	Description	Default Order
tokens	Cell array of cell arrays of strings containing the text of each token captured by regexp. (This is a cell array of strings when used with 'once'.)	5
names	Structure array containing the name and text of each <i>named</i> token captured by regexp. If there are no named tokens in expr, regexp returns a structure array with no fields.	6
	Field names of the returned structure are set to the token names, and field values are the text of those tokens. Named tokens are generated by the expression (? <tokenname>).</tokenname>	
split	Cell array containing those parts of the input string that are delimited by substrings returned when using the regexp 'match' option.	7

mode

You can specify one or more of the following modes with the regexp, regexpi, and regexprep functions. You can enable or disable any of these modes using the mode specifier keyword (e.g., 'lineanchors') or the mode flag (e.g., (?m)). Both are shown in the tables that follow. Use the keyword to enable or disable the mode for the entire string being parsed. Use the flag to both enable and disable the mode for selected pieces of the string.

For more information about modes, see "Modifying Parameters of the Search" in the MATLAB "Programming Fundamentals" documentation.

Case-Sensitivity Mode

Use the Case-Sensitivity mode to control whether or not MATLAB considers letter case when matching an expression to a string. "Example 7 — Using the Case-Sensitive Mode" on page 2-3303 illustrates this mode.

Mode Keyword	Flag	Description
matchcase'	(?-i)	Letter case must match when matching patterns to a string. (The default for regexp).
'ignorecase'	(?i)	Do not consider letter case when matching patterns to a string. (The default for regexpi).

Dot Matching Mode

Use the Dot Matching mode to control whether or not MATLAB includes the newline (\n) character when matching the dot (.) metacharacter in a regular expression. "Example 8 — Using the Dot Matching Mode" on page 2-3303 illustrates the Dot Matching mode.

Mode Keyword	Flag	Description
'dotall'	(?s)	Match dot ('.') in the pattern string with any character. (This is the default).
'dotexceptnewli	ne("?-s)	Match dot in the pattern with any character that is not a newline.

Anchor Type Mode

Use the Anchor Type mode to control whether MATLAB considers the ^ and \$ metacharacters to represent the beginning and end of a string or the beginning and end of a line. "Example 9 — Using the Anchor Type Mode" on page 2-3304 illustrates the Anchor mode.

Mode Keyword	Flag	Description
'stringanchors'	(?-m)	Match the ^ and \$ metacharacters at the beginning and end of a string. (This is the default).
'lineanchors'	(?m)	Match the ^ and \$ metacharacters at the beginning and end of a line.

Spacing Mode

Use the Spacing mode to control how MATLAB interprets space characters and comments within the parsing string. Note that spacing mode applies to the parsing string (the second input argument that contains the metacharacters (e.g., \w) and not the string being parsed. "Example 10 — Using the Spacing Mode" on page 2-3305 illustrates the Spacing mode.

Mode Keyword	Flag	Description
'literalspacin	g'(?-x)	Parse space characters and comments (the # character and any text to the right of it) in the same way as any other characters in the string. (This is the default).
'freespacing'	(?x)	Ignore spaces and comments when parsing the string. (You must use '\ ' and '\#' to match space and # characters.)

once

Specify the 'once' option to return only the first match found from the parse. This example finds four matches:

warning

Display any hidden warning messages issued by MATLAB during the execution of the command. This option only enables warnings for the one command being executed.

Output Arguments

Return Values for	Regular	Expressions
--------------------------	---------	-------------

Default Order	Description	Qualifier
1	Row vector containing the starting index of each substring of str that matches expr.	start
2	Row vector containing the ending index of each substring of str that matches expr.	end
3	Cell array containing the starting and ending indices of each substring of str that matches a token in expr. (This is a double array when used with 'once'.)	tokenExtents
4	Cell array containing the text of each substring of str that matches expr. (This is a string when used with 'once'.)	match
5	Cell array of cell arrays of strings containing the text of each token captured by regexp. (This is a cell array of strings when used with 'once'.)	tokens

Return Values for Regular Expressions (Continued	i)
--	----

Default Order	Description	Qualifier
6	Structure array containing the name and text of each <i>named</i> token captured by regexp. If there are no named tokens in expr, regexp returns a structure array with no fields.	names
	Field names of the returned structure are set to the token names, and field values are the text of those tokens. Named tokens are generated by the expression (? <tokenname>).</tokenname>	
7	Cell array containing those parts of the input string that are delimited by substrings returned when using the regexp 'match' option.	split

endIndex

Row vector containing the ending index of each substring of str that matches expr.

tokenExtents

Cell array containing the starting and ending indices of each substring of str that matches a token in expr. (This is a double array when used with 'once'.)

matchString

Cell array containing the text of each substring of str that matches expr. (This is a string when used with 'once'.)

tokenStrings

Cell array of cell arrays of strings containing the text of each token captured by regexp. (This is a cell array of strings when used with 'once'.)

tokenNames

Structure array containing the name and text of each named token captured by regexp. If there are no named tokens in expr,

regexp returns a structure array with no fields. Field names of the returned structure are set to the token names, and field values are the text of those tokens. Named tokens are generated by the expression (?<tokenName>).

splitString

Cell array containing those parts of the input string that are delimited by substrings returned when using the regexp 'match' option.

Remarks See "Regular Expressions" in the MATLAB Programming Fundamentals documentation for a listing of all regular expression elements supported by MATLAB.

Multiple Strings or Expressions

Either the str or expr argument, or both, can be a cell array of strings, according to the following guidelines:

- If str is a cell array of strings, then each of the regexp outputs is a cell array having the same dimensions as str.
- If str is a single string but expr is a cell array of strings, then each of the regexp outputs is a cell array having the same dimensions as expr.
- If both str and expr are cell arrays of strings, these two cell arrays must contain the same number of elements.

Examples Example 1 – Matching a Simple Pattern

Return a row vector of indices that match words that start with c, end with t, and contain one or more vowels between them. Make the matches insensitive to letter case (by using regexpi):

```
str = 'bat cat can car COAT court cut ct CAT-scan';
regexpi(str, 'c[aeiou]+t')
ans =
5 17 28 35
```

Example 2 – Parsing Multiple Input Strings

Return a cell array of row vectors of indices that match capital letters and white spaces in the cell array of strings str:

```
str = {'Madrid, Spain' 'Romeo and Juliet' 'MATLAB is great'};
s1 = regexp(str, '[A-Z]');
s2 = regexp(str, '\s');
```

Capital letters, '[A-Z]', were found at these str indices:

```
s1{:}
ans =
1 9
ans =
1 11
ans =
1 2 3 4 5 6
```

Space characters, $' \ s'$, were found at these str indices:

```
s2{:}
ans =
8
ans =
6 10
ans =
7 10
```

Example 3 – Selecting Return Values

Return the text and the starting and ending indices of words containing the letter x:

e = 6 22

Example 4 – Splitting the Input String

Find the substrings delimited by the ^ character:

```
s1 = ['Use REGEXP to split ^this string into ' ...
    'several ^individual pieces'];
s2 = regexp(s1, '\^', 'split');
s2(:)
ans =
    'Use REGEXP to split '
    'this string into several '
    'individual pieces'
```

The split option returns those parts of the input string that are not returned when using the 'match' option. Note that when you match the beginning or ending characters in a string (as is done in this example), the first (or last) return value is always an empty string:

For any string that has been split, you can reassemble the pieces into the initial string using the command

```
j = [splitstr; [matchstr {''}]]; [j{:}]
ans =
She sells sea shells by the seashore.
```

Example 5 – Using Tokens

Search a string for opening and closing HTML tags. Use the expression $<(\w+)$ to find the opening tag (e.g., '<tagname') and to create a token for it. Use the expression $</\1>$ to find another occurrence of the same token, but formatted as a closing tag (e.g., '</tagname>'):

```
str = ['if <code>A</code> == x<sup>2</sup>, ' ...
       '<em>disp(x)</em>']
str =
if <code>A</code> == x<sup>2</sup>, <em>disp(x)</em>
expr = '<(\w+).*?>.*?</\1>';
[tok mat] = regexp(str, expr, 'tokens', 'match');
tok{:}
ans =
    'code'
ans =
    'sup'
ans =
    'em'
mat{:}
ans =
    <code>A</code>
ans =
    <sup>2</sup>
ans =
    <em>disp(x)</em>
```

See "Tokens" in the MATLAB Programming Fundamentals documentation for information on using tokens.

Example 6 – Using Named Capture

Enter a string containing two names, the first and last names being in a different order:

```
str = sprintf('John Davis\nRogers, James')
str =
    John Davis
    Rogers, James
```

Create an expression that generates first and last name tokens, assigning the names first and last to the tokens. Call regexp to get the text and names of each token found:

```
expr = ...
'(?<first>\w+)\s+(?<last>\w+)|(?<last>\w+),\s+(?<first>\w+)';
[tokens names] = regexp(str, expr, 'tokens', 'names');
```

Examine the tokens cell array that was returned. The first and last name tokens appear in the order in which they were generated: first name-last name, then last name-first name:

```
tokens{:}
ans =
    'John' 'Davis'
ans =
    'Rogers' 'James'
```

Now examine the names structure that was returned. First and last names appear in a more usable order:

```
names(:,1)
ans =
    first: 'John'
    last: 'Davis'
names(:,2)
ans =
    first: 'James'
    last: 'Rogers'
```

Example 7 – Using the Case-Sensitive Mode

Given a string that has both uppercase and lowercase letters,

```
str = 'A string with UPPERCASE and lowercase text.';
```

Use the regexp default mode (case-sensitive) to locate only the lowercase instance of the word case:

Now disable case-sensitive matching to find both instances of case:

Match 5 letters that are followed by 'CASE'. Use the (?-i) flag to turn on case-sensitivity for the first match and (?i) to turn it off for the second:

```
M = regexp(str, {'(?-i)\w{5}(?=CASE)', ...
'(?i)\w{5}(?=CASE)'}, 'match');
M{:}
ans =
    'UPPER'
ans =
    'UPPER'
    'lower'
```

Example 8 – Using the Dot Matching Mode

Parse the following string that contains a newline (n) character:

```
str = sprintf('abc\ndef')
str =
    abc
    def
```

When you use the default mode, dotal1, MATLAB includes the newline in the characters matched:

When you use the dotexceptnewline mode, MATLAB skips the newline character:

Example 9 – Using the Anchor Type Mode

Given the following two-line string,

In stringanchors mode, MATLAB interprets the \$ metacharacter as an end-of-string specifier, and thus finds the last two words of the entire *string*:

```
regexp(str, '\w+\W\w+$', 'match', 'stringanchors')
ans =
    'second line'
```

While in lineanchors mode, MATLAB interprets \$ as an end-of-line specifier, and finds the last two words of each *line*:

```
regexp(str, '\w+\W\w+$', 'match', 'lineanchors')
ans =
    'first line' 'second line'
```

Example 10 - Using the Spacing Mode

Create a file called regexp_str.txt containing the following text.

```
(?x) # turn on freespacing.
# This pattern matches a string with a repeated letter.
\w* # First, match any number of preceding word characters.
( # Mark a token.
. # Match a character of any type.
) # Finish capturing said token.
\1 # Backreference to match what token #1 matched.
\w* # Finally, match the remainder of the word.
```

Because the first line enables freespacing mode, MATLAB ignores all spaces and comments that appear in the file. Here is the string to parse:

str = ['Looking for words with letters that ' ...
'appear twice in succession.'];

Use the pattern expression read from the file to find those words that have consecutive matching letters:

```
patt = fileread('regexp_str.txt');
regexp(str, patt, 'match')
ans =
    'Looking' 'letters' 'appear' 'succession'
```

Example 11 – Displaying Parsing Warnings

To help debug problems in parsing a string with regexp, regexpi, or regexprep, use the 'warnings' option to view all warning messages:

```
regexp('$.', '[a-]','warnings')
Warning: Unbound range.
[a-]
|
```

See Also "Regular Expressions", regexprep, regexptranslate, strfind, strcmp, strcmpi, strncmpi

Purpose	Replace string usi	ing regular expression
Syntax		str', 'expr', 'repstr') str', 'expr', 'repstr', <i>option</i> s)
Description	<pre>s = regexprep('str', 'expr', 'repstr') replaces all occurrences of the regular expression expr in string str with the string repstr. The new string is returned in s. If no matches are found, return string s is the same as input string str. You can use character representations (e.g., '\t' for tab, or '\n' for newline) in replacement string repstr. See "Regular Expressions" in the MATLAB Programming Fundamentals documentation for more information.</pre>	
		ay of strings, then the regexprep return value s is y of strings having the same dimensions as str.
	replacement strin	han one expression to match or more than one g, see the guidelines listed below under "Multiple placement Strings" on page 2-3308.
	You can capture parts of the input string as tokens and then reuse them in the replacement string. Specify the parts of the string to capture using the () operator. Specify the tokens to use in the replacement string using the operators \$1, \$2, \$N to reference the first, second, and Nth tokens captured. (See "Tokens" and the example "Using Tokens in a Replacement String" in the MATLAB Programming Fundamentals documentation for information on using tokens.)	
	<pre>s = regexprep('str', 'expr', 'repstr', options) By default, regexprep replaces all matches and is case sensitive. You can use one or more of the following options with regexprep.</pre>	
	Option	Description
	mode	See mode descriptions on the regexp reference page.
	Ν	Replace only the Nth occurrence of expr in str.

'once'

		Replace only the first occurrence of expr in str.
--	--	---

Option	Description
'ignorecase'	Ignore case when matching and when replacing.
'preservecase'	Ignore case when matching (as with 'ignorecase'), but override the case of replace characters with the case of corresponding characters in str when replacing.
'warnings'	Display any hidden warning messages issued by MATLAB during the execution of the command. This option only enables warnings for the one command being executed.

Remarks

See "Regular Expressions" in the MATLAB Programming Fundamentals documentation for a listing of all regular expression metacharacters supported by MATLAB.

Multiple Expressions or Replacement Strings

In the case of multiple expressions and/or replacement strings, regexprep attempts to make all matches and replacements. The first match is against the initial input string. Successive matches are against the string resulting from the previous replacement.

The expr and repstr inputs follow these rules:

- If expr is a cell array of strings and repstr is a single string, regexprep uses the same replacement string on each expression in expr.
- If expr is a single string and repstr is a cell array of N strings, regexprep attempts to make N matches and replacements.
- If both expr and repstr are cell arrays of strings, then expr and repstr must contain the same number of elements, and regexprep pairs each repstr element with its matching element in expr.

Examples Example 1 – Making a Case-Sensitive Replacement

Perform a case-sensitive replacement on words starting with m and ending with y:

```
str = 'My flowers may bloom in May';
pat = 'm(\w*)y';
regexprep(str, pat, 'April')
ans =
    My flowers April bloom in May
```

Replace all words starting with m and ending with y, regardless of case, but maintain the original case in the replacement strings:

```
regexprep(str, pat, 'April', 'preservecase')
ans =
    April flowers april bloom in April
```

Example 2 – Using Tokens In the Replacement String

Replace all variations of the words 'walk up' using the letters following walk as a token. In the replacement string

```
str = 'I walk up, they walked up, we are walking up.';
pat = 'walk(\w*) up';
regexprep(str, pat, 'ascend$1')
ans =
    I ascend, they ascended, we are ascending.
```

Example 3 – Operating on Multiple Strings

This example operates on a cell array of strings. It searches for consecutive matching letters (e.g., 'oo') and uses a common replacement value ('--') for all matches. The function returns a cell array of strings having the same dimensions as the input cell array:

```
str = { ....
'Whose woods these are I think I know.'; ...
'His house is in the village though;'; ...
'He will not see me stopping here'; ...
'To watch his woods fill up with snow.'};
```

```
a = regexprep(str, '(.)\1', '--', 'ignorecase')
a =
                             'Whose w--ds these are I think I know.'
                     'His house is in the vi--age though;'
                     'He wi-- not s-- me sto--ing here'
                          'To watch his w--ds fi-- up with snow.'
```

```
See Also "Regular Expressions", regexp, regexpi, regexptranslate, strfind, strcmp, strcmpi, strncmpi
```

- **Purpose** Translate string into regular expression
- **Syntax** s2 = regexptranslate(type, s1)

Description s2 = regexptranslate(type, s1) translates string s1 into a regular expression string s2 that you can then use as input into one of the MATLAB regular expression functions such as regexp. The type input can be either one of the following strings that define the type of translation to be performed. See "Regular Expressions" in the MATLAB Programming Fundamentals documentation for more information.

Туре	Description
'escape'	Translate all special characters (e.g., ' $$'$, '.', '?', '[') in string s1 so that they are treated as literal characters when used in the regexp and regexprep functions. The translation inserts an escape character ('\') before each special character in s1. Return the new string in s2.
'wildcard'	Translate all wildcard and '.' characters in string s1 so that they are treated as literal wildcards and periods when used in the regexp and regexprep functions. The translation replaces all instances of '*' with '.*', all instances of '?' with '.', and all instances of '.' with '\.'. Return the new string in s2.

Examples Example 1 – Using the 'escape' Option

Because regexp interprets the sequence '\n' as a newline character, it cannot locate the two consecutive characters '\' and 'n' in this string:

```
str = 'The sequence \n generates a new line';
pat = '\n';
regexp(str, pat)
ans =
   []
```

To have regexp interpret the expression expr as the characters `` and `n', first translate the expression using regexptranslate:

```
pat2 = regexptranslate('escape', pat)
pat2 =
     \\n
regexp(str, pat2)
ans =
     14
```

Example 2 – Using 'escape' In a Replacement String

Replace the word 'walk' with 'ascend' in this string, treating the characters '\$1' as a token designator:

```
str = 'I walk up, they walked up, we are walking up.';
pat = 'walk(\w*) up';
regexprep(str, pat, 'ascend$1')
ans =
    I ascend, they ascended, we are ascending.
```

Make another replacement on the same string, this time treating the '\$1' as literal characters:

```
regexprep(str, pat, regexptranslate('escape', 'ascend$1'))
ans =
    I ascend$1, they ascend$1, we are ascend$1.
```

Example 3 – Using the 'wildcard' Option

Given the following string of filenames, pick out just the MAT-files. Use regexptranslate to interpret the '*' wildcard as '\w+' instead of as a regular expression quantifier:

```
'test1.mat' 'myfile.mat' 'jan30.mat'
To see the translation, you can type
    regexptranslate('wildcard','*.mat')
    ans =
        \w+\.mat
See Also "Regular Expressions", regexp, regexpi, regexprep
```

registerevent

Purpose	Associate event handler for COM object event at run time
Syntax	h.registerevent(eventhandler) registerevent(h, eventhandler)
Description	h.registerevent(eventhandler) registers event handler routines with their corresponding events. The eventhandler argument can be either a string that specifies the name of the event handler function, or a function handle that maps to that function. Strings used in the eventhandler argument are not case sensitive.
	registerevent(h, eventhandler) is an alternate syntax.
	COM functions are available on Microsoft Windows systems only.
Examples	Show events in the MATLAB sample control:
	<pre>f = figure ('position', [100 200 200 200]); h = actxcontrol ('mwsamp.mwsampctrl.2', [0 0 200 200], f); h.events</pre>
	MATLAB displays all events associated with the instance of the control (output is formatted):
	<pre>Click = void Click() DblClick = void DblClick() MouseDown = void MouseDown(int16 Button, int16 Shift, Variant x, Variant y) Event_Args = void Event_Args(int16 typeshort, int32 typelong, double typedouble, string typestring, bool typebool)</pre>

Register all events with the same event handler routine, sampev:

```
h.registerevent('sampev');
h.eventlisteners
```

MATLAB displays:

```
ans =
    'Click' 'sampev'
    'DblClick' 'sampev'
    'MouseDown' 'sampev'
    'Event_Args' 'sampev'
```

Register individual events:

```
%Unregister existing events
h.unregisterallevents;
%Register specific events
h.registerevent({'click' 'myclick'; ...
        'dblclick' 'my2click'});
h.eventlisteners
```

MATLAB displays:

ans = 'click' 'myclick' 'dblclick' 'my2click'

Register events using a function handle (@sampev) instead of the function name:

h = actxcontrol('mwsamp.mwsampctrl.2', [0 0 200 200]); registerevent(h, @sampev);

- See Also events (COM) | eventlisteners | unregisterevent | unregisterallevents | isevent
- **How To** "Writing Event Handlers"

rehash

Purpose	Refresh function and file system path caches
Syntax	rehash rehash path rehash toolbox rehash pathreset rehash toolboxreset rehash toolboxcache
Description	rehash with no arguments updates the MATLAB lis

rehash with no arguments updates the MATLAB list of known files and classes for directories on the search path that are not in *matlabroot*/toolbox. It compares the timestamps for loaded functions against their timestamps on disk. It clears loaded functions if the files on disk are newer. All of this normally happens each time MATLAB displays the Command Window prompt. Use rehash with no arguments only when you run a program file that updates another program file, and the calling file needs to reuse the updated version of the second file before the calling file has finished running.

rehash path performs the same updates as rehash, but uses a different technique for detecting the files and directories that require updates. Run rehash path only if you receive a warning during MATLAB startup notifying you that MATLAB could not tell if a directory has changed, and you encounter problems with MATLAB not using the most current versions of your program files.

rehash toolbox performs the same updates as rehash path, except it updates the list of known files and classes for *all* directories on the search path, including those in *matlabroot*/toolbox. Run rehash toolbox when you change, add, or remove files in *matlabroot*/toolbox during a session. Typically, you should not make changes to files and directories in *matlabroot*/toolbox.

rehash **pathreset** performs the same updates as rehash **path**, and also ensures the known files and classes list follows precedence rules for shadowed functions.

	rehash toolboxreset performs the same updates as rehash toolbox and also ensures the known files and classes list follows precedence rules for shadowed functions.			
	rehash toolboxcache performs the same updates as rehash toolbox, and also updates the cache file. This is the equivalent of clicking the Update Toolbox Path Cache button in the General Preferences dialog box.			
See Also	addpath, clear, matlabroot, path, rmpath			
	"Toolbox Path Caching in the MATLAB Program" and "Using the MATLAB Search Path" in the MATLAB Desktop Tools and Development Environment documentation			

release

Purpose	Release COM interface
Syntax	h.release release(h)
Description	h.release releases the interface and all resources used by the interface. You must release the handle when you are done with the interface. A released interface is no longer valid. MATLAB generates an error if you try to use an object that represents that interface.
	release(h) is an alternate syntax.
	Releasing the interface does not delete the control itself (see the delete function), since other interfaces on that object might still be active.
	COM functions are available on Microsoft Windows systems only.
Examples	1 Create an instance of a Microsoft Calendar control. Get a TitleFont interface and use it to change the appearance of the calendar title font:
	<pre>f = figure('position',[300 300 500 500]); cal = actxcontrol('mscal.calendar', [0 0 500 500], f);</pre>
	TFont = cal.TitleFont; TFont.Name = 'Viva BoldExtraExtended';
	TFont.Bold = 0;
	2 After working with the title font, release the TitleFont interface:
	TFont.release;
	3 Delete the cal object and the figure window:
	cal.delete; delete(f); clear f;
See Also	delete (COM) actxcontrol actxserver

How To • Releasing Interfaces

Purpose	Equality and sorting of handle objects
Syntax	TF = eq(H1,H2) TF = ne(H1,H2) TF = lt(H1,H2) TF = le(H1,H2) TF = gt(H1,H2) TF = ge(H1,H2)
Description	<pre>TF = eq(H1,H2) TF = ne(H1,H2) TF = lt(H1,H2) TF = le(H1,H2) TF = gt(H1,H2) TF = ge(H1,H2)</pre>

For each pair of input arrays (H1 and H2), a logical array of the same size is returned in which each element is an element-wise equality or comparison test result. These methods perform scalar expansion in the same way as the MATLAB built-in functions. See relationaloperators for more information.

You can make the following assumptions about the result of a handle comparison:

- The same two handles always compare as equal and the repeated comparison of any two handles always yields the same result in the same MATLAB session.
- Different handles are always not-equal.
- The order of handle values is purely arbitrary and has no connection to the state of the handle objects being compared.
- If the input arrays belong to different classes (including the case where one input array belongs to a non-handle class such as double) then the comparison is always false.

- If a comparison is made between a handle object and an object of a dominant class, the method of the dominant class is invoked. You should generally test only like objects because a dominant class might not define one of these methods.
 - An error occurs if the input arrays are not the same size and neither is scalar.

See Also handle, meta.class

Purpose	Remainder after division					
Syntax	R = rem(X,Y)					
Description	$R = rem(X,Y)$ if $Y \sim = 0$, returns $X - n.*Y$ where $n = fix(X./Y)$. If Y is not an integer and the quotient X./Y is within roundoff error of an integer, then n is that integer. The inputs X and Y must be real arrays of the same size, or real scalars.					
	The following are true by convention:					
	• rem(X,O) is NaN					
	• rem(X,X) for X~=0 is 0					
	• $rem(X,Y)$ for X~=Y and Y~=O has the same sign as X.					
Remarks	mod(X,Y) for X~=Y and Y~=O has the same sign as Y.					
	rem(X,Y) and mod(X,Y) are equal if X and Y have the same sign, but differ by Y if X and Y have different signs.					
	The rem function returns a result that is between 0 and $sign(X)*abs(Y)$. If Y is zero, rem returns NaN.					
See Also	mod					

remove (Map)

Purpose	Remove key-value pairs from containers.Map
Syntax	remove(M, keys)
Description	remove(M, keys) erases all specified keys, and the values associated with them, from Map object M.keys can be a scalar key or a cell array of keys.
	Using remove changes the count of the elements in the map.
	Read more about Map Containers in the MATLAB Programming Fundamentals documentation.
Examples	Create a Map object containing the names of several US states and the capital city of each:
	US_Capitals = containers.Map({'Arizona', 'Nebraska', 'Nevada', 'New York', 'Georgia', 'Alaska', 'Vermont', 'Oregon'}, {'Phoenix', 'Lincoln', 'Carson City', 'Albany', 'Atlanta', 'Juneau', 'Montpelier', 'Salem'});
	After checking how many keys there are in the US_Capitals map, remove the key-value pair with key name Oregon from it:
	US_Capitals.Count ans = 8
	<pre>remove(US_Capitals, 'Oregon');</pre>
	US_Capitals.Count ans = 7

Remove three more key-value pairs from the map:

```
remove(US_Capitals, {'Nebraska', 'Nevada', 'New York'});
US_Capitals.Count
ans =
4
```

See Also containers.Map, keys(Map), values(Map), size(Map), length(Map)isKey(Map),handle

removets

Purpose	Remove timeseries objects from tscollection object						
Syntax	<pre>tsc = removets(tsc,Name)</pre>						
Description	<pre>tsc = removets(tsc,Name) removes one or more timeseries objects with the name specified in Name from the tscollection object tsc. Name can either be a string or a cell array of strings.</pre>						
Examples	The following example shows how to remove a time series from a tscollection.						
	1 Create two timeseries objects, ts1 and ts2.						
	ts1=timeseries([1.1 2.9 3.7 4.0 3.0],1:5,'name','acceleration'); ts2=timeseries([3.2 4.2 6.2 8.5 1.1],1:5,'name','speed');						
	2 Create a tscollection object tsc, which includes ts1 and ts2.						
	<pre>tsc=tscollection({ts1 ts2});</pre>						
	3 To view the members of tsc, type the following at the MATLAB prompt:						
	tsc						
	The response is						
	Time Series Collection Object: unnamed						
	Time vector characteristics						
	Start time1 secondsEnd time5 seconds						
	Member Time Series Objects:						

acceleration speed

The members of tsc are listed by name at the bottom: acceleration and speed. These are the Name properties of ts1 and ts2, respectively.

4 Remove ts2 from tsc.

tsc=removets(tsc,'speed');

5 To view the current members of tsc, type the following at the MATLAB prompt:

tsc

The response is

Time Series Collection Object: unnamed

Time vector characteristics

Start time1 secondsEnd time5 seconds

Member Time Series Objects: acceleration

The remaining member of tsc is acceleration. The timeseries speed has been removed.

See Also addts, tscollection

Purpose	Rename file on FTP server						
Syntax	rename(f,'oldname','newname')						
Description	rename(f, 'oldname', 'newname') changes the name of the file oldname to newname in the current directory of the FTP server f, where f was created using ftp.						
Examples	Connect to server testsite, view the contents, and change the name of testfile.m to showresults.m.						
	test=ftp('ftp.testsite.com'); dir(test) testfile.m rename(test,'testfile.m','showresults.m') dir(test) showresults.m						
See Also	dir (ftp), delete (ftp), ftp, mget, mput						

repmat

Purpose	Replicate and tile array							
Syntax	<pre>B = repmat(A,m,n) B = repmat(A,[m n]) B = repmat(A,[m n p])</pre>							
Description	B = repmat(A,m,n) creates a large matrix B consisting of an m-by-n tiling of copies of A. The size of B is [size(A,1)*m, (size(A,2)*n]. The statement repmat(A,n) creates an n-by-n tiling.							
	<pre>B = repmat(A,[m n]) accomplishes the same result as repmat(A,m</pre>	, n).						
	B = repmat(A,[m n p]) produces a multidimensional array B composed of copies of A. The size of B is [size(A,1)*m, size(A,2)*n size(A,3)*p,].	١,						
Remarks	repmat(A,m,n), when A is a scalar, produces an m-by-n matrix filled w A's value and having A's class. For certain values, you can achieve same results using other functions, as shown by the following examp	the						
	 repmat(NaN,m,n) returns the same result as NaN(m,n). 							
	• repmat(single(inf),m,n) is the same as inf(m,n,'single').							
	 repmat(int8(0),m,n) is the same as zeros(m,n,'int8'). 							
	 repmat(uint32(1),m,n) is the same as ones(m,n,'uint32'). 							
	 repmat(eps,m,n) is the same as eps(ones(m,n)). 							
Examples	In this example, repmat replicates 12 copies of the second-order iden matrix, resulting in a "checkerboard" pattern.	itity						
	<pre>B = repmat(eye(2),3,4)</pre>							
	В =							
	1 0 1 0 1 0 1 0							
	1 0 1 0 1 0 1 0							

	1	(0	1	0	1	1 0 1	1	
	-			-		-		-	natrix of NaNs.
See Also	reshape, I	bsxfun	n, NaN,	Inf,o	nes, ze	ros			

Purpose	Select or interpolate timeseries data using new time vector
Syntax	ts = resample(ts,Time) ts = resample(ts,Time,interp_method) ts = resample(ts,Time,interp_method,code)
Description	<pre>ts = resample(ts,Time) resamples the timeseries object ts using the new Time vector. When ts uses date strings and Time is numeric, Time is treated as specified relative to the ts.TimeInfo.StartDate property and in the same units that ts uses. The resample operation uses the default interpolation method, which you can view by using the getinterpmethod(ts) syntax.</pre>
	<pre>ts = resample(ts,Time,interp_method) resamples the timeseries object ts using the interpolation method given by the string interp_method. Valid interpolation methods include 'linear' and 'zoh' (zero-order hold).</pre>
	<pre>ts = resample(ts,Time,interp_method,code) resamples the timeseries object ts using the interpolation method given by the string interp_method. The integer code is a user-defined Quality code for resampling, applied to all samples.</pre>
Examples	The following example shows how to resample a timeseries object.
	l Create a timeseries object.
	ts=timeseries([1.1 2.9 3.7 4.0 3.0],1:5,'Name','speed');
	2 Transpose ts to make the data columnwise.
	ts=transpose(ts)
	The display in the MATLAB Command Window is
	Time Series Object: speed
	Time vector characteristics

	Length		5	
	Start time		1 secon	ds
	End time		5 secon	ds
Data	characterist	ics		
	Interpolatio Size Data type	on method	linear [5 1] double	
Time		Data		Quality
1 2		1.1 2.9		
3		3.7		
4		4		
5		3		

Note that the interpolation method is set to linear, by default.

3 Resample ts using its default interpolation method.

res_ts=resample(ts,[1 1.5 3.5 4.5 4.9])

The resampled time series displays as follows:

Time Series Object: speed

Time vector characteristics

Length5Start time1 secondsEnd time4.900000e+000 seconds

Data characteristics

	Interpolatior Size Data type	n method	linear [5 1] double	
Time	C	Data		Quality
1 1.5 3.5	2	3.85		
4.5 4.9	-	3.5 3.1		

See Also getinterpmethod, setinterpmethod, synchronize, timeseries

Purpose	Select or interpolate data in tscollection using new time vector
Syntax	tsc = resample(tsc,Time) tsc = resample(tsc,Time,interp_method) tsc = resample(tsc,Time,interp_method,code)
Description	<pre>tsc = resample(tsc,Time) resamples the tscollection object tsc on the new Time vector. When tsc uses date strings and Time is numeric, Time is treated as numerical specified relative to the tsc.TimeInfo.StartDate property and in the same units that tsc uses. The resample method uses the default interpolation method for each time series member.</pre>
	<pre>tsc = resample(tsc,Time,interp_method) resamples the tscollection object tsc using the interpolation method given by the string interp_method. Valid interpolation methods include 'linear' and 'zoh' (zero-order hold).</pre>
	tsc = resample(tsc,Time,interp_method,code) resamples the tscollection object tsc using the interpolation method given by the string interp_method. The integer code is a user-defined quality code for resampling, applied to all samples.
Examples	The following example shows how to resample a tscollection that consists of two timeseries members.
	1 Create two timeseries objects.
	ts1=timeseries([1.1 2.9 3.7 4.0 3.0],1:5,'name','acceleration'); ts2=timeseries([3.2 4.2 6.2 8.5 1.1],1:5,'name','speed');
	2 Create a tscollection tsc.
	<pre>tsc=tscollection({ts1 ts2});</pre>
	The time vector of the collection tsc is [1:5], which is the same as

for ts1 and ts2 (individually).

3 Get the interpolation method for acceleration by typing tsc.acceleration MATLAB responds with Time Series Object: acceleration Time vector characteristics Length 5 Start time 1 seconds End time 5 seconds Data characteristics Interpolation method linear [1 1 5] Size Data type double **4** Set the interpolation method for speed to zero-order hold by typing setinterpmethod(tsc.speed,'zoh') MATLAB responds with Time Series Object: acceleration Time vector characteristics Length 5 Start time 1 seconds End time 5 seconds

Data characteristics

Interpolation method	zoh
Size	[1 1 5]
Data type	double

5 Resample the time-series collection tsc by individually resampling each time-series member of the collection and using its interpolation method.

res_tsc=resample(tsc,[1 1.5 3.5 4.5 4.9])

See Also getinterpmethod, setinterpmethod, tscollection

reset

Purpose	Reset graphics object properties to their defaults
Syntax	reset(h)
Description	<pre>reset(h) resets all properties having factory defaults on the object identified by h. To see the list of factory defaults, use the statement get(0, 'factory')</pre>
	If h is a figure, the MATLAB software does not reset Position, Units, WindowStyle, or PaperUnits. If h is an axes, MATLAB does not reset Position and Units.
Examples	<pre>reset(gca) resets the properties of the current axes. reset(gcf) resets the properties of the current figure.</pre>
See Also	cla, clf, gca, gcf, hold "Object Manipulation" on page 1-110 for related functions

Purpose	Reset random stream						
Class	@RandStream						
Syntax	reset(s) reset(s,seed)						
Description	<pre>reset(s) resets the generator for the random stream s to its initial internal state. This is similar to clearing s and recreating it using RandStream('type',), except reset does not set the stream's RandnAlg, Antithetic, and FullPrecision properties to their original values.</pre>						
	reset(s,seed) resets the generator for the random stream s to the initial internal state corresponding to the seed seed. Resetting a stream's seed can invalidate independence with other streams.						
	Note Resetting a stream should be used primarily for reproducing results.						
Examples	1 Create a random stream object.						
	s=RandStream('mt19937ar')						
	2 Make it the default stream.						
	RandStream.setDefaultStream(s)						
	3 Reset the stream object you just created and generate 5 uniform random values using the rand method.						
	rand(s,1,5)						
	ans =						
	0.3631 0.4048 0.1490 0.9438 0.1247						

4 Reset the stream.

reset(s)

5 Generate the same 5 random values from the default stream.

rand(s,1,5) ans = 0.3631 0.4048 0.1490 0.9438 0.1247

See Also

@RandStream

Purpose	Reshape array					
Syntax	<pre>B = reshape(A,m,n) B = reshape(A,m,n,p,) B = reshape(A,[m n p]) B = reshape(A,,[],) B = reshape(A,siz)</pre>					
Description	B = reshape(A,m,n) returns the m-by-n matrix B whose elements are taken column-wise from A. An error results if A does not have m*n elements.					
	B = reshape(A,m,n,p,) or B = reshape(A,[m n p]) returns an n-dimensional array with the same elements as A but reshaped to have the size m-by-n-by-p-by The product of the specified dimensions, m*n*p*, must be the same as prod(size(A)).					
	<pre>B = reshape(A,,[],) calculates the length of the dimension represented by the placeholder [], such that the product of the dimensions equals prod(size(A)). The value of prod(size(A)) must be evenly divisible by the product of the specified dimensions. You can use only one occurrence of [].</pre>					
	B = reshape(A,siz) returns an n-dimensional array with the same elements as A, but reshaped to siz, a vector representing the dimensions of the reshaped array. The quantity prod(siz) must be the same as prod(size(A)).					
Examples	Reshape a 3-by-4 matrix into a 2-by-6 matrix.					
	$A = \begin{bmatrix} 1 & 4 & 7 & 10 \\ 2 & 5 & 8 & 11 \\ 3 & 6 & 9 & 12 \end{bmatrix}$ B = reshape(A,2,6) B =					

		1	3	5	7	9	11
		2	4	6	8	10	12
	В =	= res	hape(A,2,[])		
	B =						
		1	3	5	7	9	11
		2	4	6	8	10	12
See Also	shift	dim, s	squeez	ze,ci	rcshi	ft, pe	rmute, repmat

The colon operator :

Purpose Convert between partial fraction expansion and polynomial coefficients

Syntax [r,p,k] = residue(b,a)
[b,a] = residue(r,p,k)

Description The residue function converts a quotient of polynomials to pole-residue representation, and back again.

[r,p,k] = residue(b,a) finds the residues, poles, and direct term of a partial fraction expansion of the ratio of two polynomials, b(s) and a(s), of the form

$$\frac{b(s)}{a(s)} = \frac{b_1 s^m + b_2 s^{m-1} + b_3 s^{m-2} + \dots + b_{m+1}}{a_1 s^n + a_2 s^{n-1} + a_3 s^{n-2} + \dots + a_{n+1}}$$

where b_{i} and a_{i} are the jth elements of the input vectors **b** and **a**.

[b,a] = residue(r,p,k) converts the partial fraction expansion back to the polynomials with coefficients in b and a.

Definition If there are no multiple roots, then

$$\frac{b(s)}{a(s)} = \frac{r_1}{s - p_1} + \frac{r_2}{s - p_2} + \dots + \frac{r_n}{s - p_n} + k(s)$$

The number of poles n is

n = length(a) - 1 = length(r) = length(p)

The direct term coefficient vector is empty if length(b) < length(a); otherwise

length(k) = length(b) - length(a) + 1

If $p(j) = \ldots = p(j+m-1)$ is a pole of multiplicity m, then the expansion includes terms of the form

residue

$$\frac{r_j}{s-p_j} + \frac{r_{j+1}}{(s-p_j)^2} + \dots + \frac{r_{j+m-1}}{(s-p_j)^m}$$

Arguments	b,a	Vectors that specify the coefficients of the polynomials in descending powers of \boldsymbol{s}
	r	Column vector of residues
	р	Column vector of poles
	k	Row vector of direct terms
Algorithm	the direc	btains the poles with roots. Next, if the fraction is nonproper, ct term k is found using deconv, which performs polynomial ision. Finally, the residues are determined by evaluating the

Limitations Numerically, the partial fraction expansion of a ratio of polynomials represents an ill-posed problem. If the denominator polynomial, a(s), is near a polynomial with multiple roots, then small changes in the data, including roundoff errors, can make arbitrarily large changes in the resulting poles and residues. Problem formulations making use of state-space or zero-pole representations are preferable.

computes the residues at the repeated root locations.

polynomial with individual roots removed. For repeated roots, resi2

Examples If the ratio of two polynomials is expressed as

$$\frac{b(s)}{a(s)} = \frac{5s^3 + 3s^2 - 2s + 7}{-4s^3 + 8s + 3}$$

then

and you can calculate the partial fraction expansion as

```
[r, p, k] = residue(b,a)
r =
    -1.4167
    -0.6653
    1.3320
p =
    1.5737
    -1.1644
    -0.4093
k =
    -1.2500
```

Now, convert the partial fraction expansion back to polynomial coefficients.

```
[b,a] = residue(r,p,k)
b =
    -1.2500 -0.7500 0.5000 -1.7500
a =
    1.0000 -0.0000 -2.0000 -0.7500
```

The result can be expressed as

$$\frac{b(s)}{a(s)} = \frac{-1.25s^3 - 0.75s^2 + 0.50s - 1.75}{s^3 - 2.00s - 0.75}$$

Note that the result is normalized for the leading coefficient in the denominator.

See Also deconv, poly, roots

References [1] Oppenheim, A.V. and R.W. Schafer, *Digital Signal Processing*, Prentice-Hall, 1975, p. 56.

Purpose	Restore default search path
GUI Alternatives	As an alternative to the restoredefaultpath function, use the Set Path dialog box.
Syntax	restoredefaultpath restoredefaultpath; matlabrc
Description	restoredefaultpath sets the search path to include only folders for installed products from The MathWorks. Use restoredefaultpath when you are having problems with the search path.
	restoredefaultpath; matlabrc sets the search path to include only folders for installed products from The MathWorks and corrects search path problems encountered during startup.
	MATLAB does not support issuing restoredefaultpath from a UNC path name. Doing so might result in MATLAB being unable to find files on the search path. If you do issue restoredefaultpath from a UNC path name, restore the expected behavior by changing the current folder to an absolute path, and then reissuing restoredefaultpath.
See Also	addpath, genpath, matlabrc, rmpath, savepath Topics in the User Guide:
	 "Recovering from Problems with the Search Path" "Using the MATLAB Search Path"

Purpose	Reissue error				
	Note As of version 7.5, MATLAB supports error handling that is based on the MException class. Calling rethrow with a structure argument, as described on this page, is now replaced by calling rethrow with an MException object, as described on the reference page for rethrow(MException). rethrow called with a structure input will be removed in a future version.				
Syntax	rethrow(errorStruct)				
Description	rethrow(errorStruct) reissues the error specified by errorStruct. The currently running function terminates and control returns to the keyboard (or to any enclosing catch block). The errorStruct argument must be a MATLAB structure containing at least the message and identifier fields:				
	Fieldname	Description			
	message	Text of the error message			
	identifier	Message identifier of the error message			
	stack	Information about the error from the program stack			
Remarks	information on the The errorStructor to the output of the stack of the rether	entifiers" in the MATLAB documentation for more he syntax and usage of message identifiers. t input can contain the field stack, identical in format he dbstack command. If the stack field is present, the rown error will be set to that value. Otherwise, the to the line at which the rethrow occurs.			

Examples rethrow is usually used in conjunction with try-catch statements to reissue an error from a catch block after performing catch-related operations. For example,

```
try
    do_something
catch
    do_cleanup
    rethrow(previous_error)
end
```

See Also rethrow(MException), throw(MException), throwAsCaller(MException), try, catch, error, assert, dbstop

rethrow (MException)

Purpose Reissue existing excepti	on	
---	----	--

Syntax rethrow(exception)

Description rethrow(*exception*) forces an exception (i.e., error report) to be reissued by MATLAB after the error reporting process has been temporarily suspended to diagnose or remedy the problem. MATLAB typically responds to errors by terminating the currently running program. Errors occurring within a try block, however, bypass this mechanism and transfer control of the program to error handling code in the catch block instead. This enables you to write your own error handling procedures for parts of your program that require them.

The *exception* input is a scalar object of the MException class that contains information about the cause and location of the error.

The code segment below shows the format of a typical try-catch statement.

try	try block
program-code	
program-code	
:	V
catch exception	catch block
error-handling code	
:	
rethrow(exception)	V
end	

An error detected within the try block causes MATLAB to enter the corresponding catch block. The error record constructed by MATLAB in the process of reporting this error passes to the catch command in the statement

catch exception

Error handling code within the catch block uses the information in the error record to address the problem in some predefined manner. The

catch block shown here ends with a rethrow statement which throws the exception returned in the catch statement, and then terminates the function:

```
rethrow(exception)
```

The most significant difference between rethrow and other MATLAB functions that throw exceptions is in how rethrow handles a piece of the exception record called the *stack*. The stack keeps a record of where the error occurred and what functions were called in the process. It is a struct array composed of the following fields, where each element of the array represents an exception:

Fields of the Exception Stack	Description
line	Line number from which the exception was thrown.
name	Name of the function being executed at the time.
file	Name of the file containing that function.

Functions such as error, assert, or throw, create the stack with the location from which they were executed. Calling rethrow, however, preserves information from the original exception. In doing so, rethrow enables you to retrace the path taken to the source of the error.

Remarks

There are four ways to throw an exception in MATLAB (see the list below). Use the first of these when testing the outcome of some action for failure and reporting the failure to MATLAB. Use one of the remaining three techniques to throw an existing exception.

1 Test the result of some action taken by your program. If the result is found to be incorrect or unexpected, compose an appropriate message and message identifier, and pass these to MATLAB using the error function.

- 2 Reissue the original exception by throwing the initial error record unmodified. Use the MException rethrow method to do this.
- **3** Collect additional information on the cause of the error, store it in a new or modified error record, and issue a new exception based on that record. Use the MException addCause and throw methods to do this.
- **4** Make it appear that the error originated in the caller of the currently running function. Use the MException throwAsCaller method to do this.

rethrow can only issue a previously caught exception. Calling rethrow on an exception that was not previously thrown is an error.

Examples This example shows the difference between using throw and rethrow at the end of a catch block. The combineArrays function vertically concatenates arrays A and B. When the two arrays have rows of unequal length, the function throws an error.

The first time you run the function, comment out the rethrow command at the end of the catch block so that the function calls throw instead:

```
function C = combineArrays(A, B)
try
    catAlongDim1(A, B); % Line 3
catch exception
    throw(exception) % Line 5
    % rethrow(exception) % Line 6
end
function catAlongDim1(V1, V2)
    C = cat(1, V1, V2); % Line 10
```

When MATLAB throws the exception, it reports an error on line 5 which is the line that calls throw. In some cases, that might be what you want but, in this case, it does not show the true source of the error.

A = 4:3:19; B = 3:4:19;

```
combineArrays(A, B)
** ERROR: Incompatible array sizes 6 and 5 **
??? Error using ==> combineArrays at 7
CAT arguments dimensions are not consistent.
```

Make the following changes to combineArrays.m so that you use rethrow instead:

% throw(exception)	%	Line	7
rethrow(exception)	%	Line	8

Run the function again. This time, line 12 is the first line reported which is where the MATLAB concatenation function cat was called and the exception originated. The next error reported is on line 3 which is where the call to catAlongDim1 was called:

```
** ERROR: Incompatible array sizes 6 and 5 **
??? Error using ==> cat
CAT arguments dimensions are not consistent.
Error in ==> combineArrays>catAlongDim1 at 12
    C = cat(1, V1, V2);
Error in ==> combineArrays at 3
    catAlongDim1(A, B);
```

See Also try, catch, error, assert, MException, throw(MException), throwAsCaller(MException), addCause(MException), getReport(MException), last(MException)

return

Purpose	Return to invoking function
Syntax	return
Description	return causes a normal return to the invoking function or to the keyboard. It also terminates keyboard mode.
Examples	This determinant function uses return to handle the special case of an empty matrix:
	<pre>function d = det(A) %DET det(A) is the determinant of A. if isempty(A) d = 1; return else end</pre>
See Also	break, continue, disp, end, error, for, if, keyboard, switch, while

Tiff.rewriteDirectory

Purpose	Write modified metadata to existing IFD
Syntax	<pre>tiffobj.rewriteDirectory()</pre>
Description	tiffobj.rewriteDirectory() writes modified metadata (tag) data to an existing directory. Use this tag when you want to change the value of a tag in an existing image file directory.
Examples	Open a Tiff object for modification and modify the value of a tag. Replace myfile.tif with the name of a TIFF file on your MATLAB path.
	t = Tiff('myfile.tif', 'r'); % Modify the value of a tag. t.setTag('Software','MATLAB'); t.rewriteDirectory();
	References
	This method corresponds to the TIFFRewriteDirectory function in the LibTIFF C API. To use this method, you must be familiar with LibTIFF version 3.7.1, as well as the TIFF specification and technical notes. View this documentation at LibTIFF - TIFF Library and Utilities.
See Also	Tiff.writeDirectory
Tutorials	"Exporting Image Data and Metadata to TIFF Files""Reading Image Data and Metadata from TIFF Files"

rgb2hsv

Purpose	Convert RGB colormap to HSV colormap
Syntax	cmap = rgb2hsv(M) hsv_image = rgb2hsv(rgb_image)
Description	cmap = rgb2hsv(M) converts an RGB colormap M to an HSV colormap $cmap$. Both colormaps are <i>m</i> -by-3 matrices. The elements of both colormaps are in the range 0 to 1.
	The columns of the input matrix M represent intensities of red, green, and blue, respectively. The columns of the output matrix cmap represent hue, saturation, and value, respectively.
	hsv_image = rgb2hsv(rgb_image) converts the RGB image to the equivalent HSV image. RGB is an m-by-n-by-3 image array whose three planes contain the red, green, and blue components for the image. HSV is returned as an m-by-n-by-3 image array whose three planes contain the hue, saturation, and value components for the image.
See Also	brighten, colormap, hsv2rgb, rgbplot
	"Color Operations" on page 1-108 for related functions

Purpose	Convert RGB image to indexed image
Syntax	[X,map] = rgb2ind(RGB, n) X = rgb2ind(RGB, map) [X,map] = rgb2ind(RGB, tol) [] = rgb2ind(, dither_option)
Description	<code>rgb2ind</code> converts RGB images to indexed images using one of these methods:
	Uniform quantization
	Minimum variance quantization
	Colormap approximation
	For all these methods, rgb2ind also dithers the image unless you specify 'nodither' for dither_option.
	[X,map] = rgb2ind(RGB, n) converts the RGB image to an indexed image X using minimum variance quantization. map contains at most n colors. n must be less than or equal to 65,536.
	X = rgb2ind(RGB, map) converts the RGB image to an indexed image X with colormap map by matching colors in RGB with the nearest color in the colormap map. size(map,1) must be less than or equal to 65,536.
	[X,map] = rgb2ind(RGB, tol) converts the RGB image to an indexed image X using uniform quantization. map contains at most (floor(1/tol)+1)^3 colors. tol must be between 0.0 and 1.0.
	[] = rgb2ind(, dither_option) enables or disables dithering. dither_option is a string that can have one of these values.

	'dither' (default)	dithers, if necessary, to achieve better color resolution at the expense of spatial resolution.
	'nodither'	maps each color in the original image to the closest color in the new map. No dithering is performed.
		ltant image X are indexes into the colormap nathematical processing, such as filtering
Class Support	the length of map is less than	ass uint8, uint16, single, or double. If n or equal to 256, the output image is of output image is of class uint16.
Remarks	image. This method involves cubes of length tol. For example,	uses uniform quantization to convert the s cutting the RGB color cube into smaller mple, if you specify a tol of 0.1, the edges of length of the RGB cube. The total number
	n = (floor(1/tol)+1)^;	3
	maximum length of the color	le color in the output image. Therefore, the rmap is n. rgb2ind removes any colors that age, so the actual colormap can be much
	method involves cutting the necessarily cubes) of differen distributed in the image. If	es minimum variance quantization. This RGB color cube into smaller boxes (not at sizes, depending on how the colors are the input image actually uses fewer colors y, the output colormap is also smaller.

If you specify map, rgb2ind uses colormap mapping, which involves finding the colors in map that best match the colors in the RGB image.


Examples

RGB = imread('peppers.png');
[X,map] = rgb2ind(RGB,128);
figure, imshow(X,map)



See Also cmunique, dither, imapprox, ind2rgb


rgbplot



Examples Plot the RGB values of the copper colormap.

rgbplot(copper)

rgbplot





colormap

"Color Operations" on page 1-108 for related functions

ribbon

Purpose

Ribbon plot



GUI Alternatives	To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.
Syntax	ribbon(Y) ribbon(X,Y) ribbon(X,Y,width) ribbon(axes_handle,) h = ribbon()
Description	<pre>ribbon(Y) plots the columns of Y as undulating three-dimensional ribbons of uniform width using X = 1:size(Y,1). Ribbons advance along the x-axis centered on tick marks at unit intervals, three-quarters of a unit in width. Ribbons are assigned colors from the current colormap in sequence from minimum X to maximum X (the axes colororder property, used by plot and plot3, does not apply to ribbon or other surface plots).</pre>

ribbon(X,Y) plots X versus the columns of Y as three-dimensional strips. X and Y are vectors of the same size or matrices of the same size. Additionally, X can be a row or a column vector, and Y a matrix with length(X) rows. ribbon(X,Y) is the same as plot(X,Y) except that the columns of Y are plotted as separated ribbons in 3-D. The y and z-axes of ribbon(X,Y) correspond to the x and y-axes of plot(X,Y).


ribbon(X,Y,width) specifies the width of the ribbons. The default is 0.75. If width = 1, the ribbons touch, leaving no space between them when viewed down the z-axis. If width > 1, ribbons overlap and can intersect.

ribbon(axes_handle,...) plots into the axes with handle axes_handle instead of the current axes (gca).

h = ribbon(...) returns a vector of handles to surface graphics objects. ribbon returns one handle per strip.

Examples Create a ribbon plot of the peaks function.

```
[x,y] = meshgrid(-3:.5:3,-3:.1:3);
z = peaks(x,y);
ribbon(y,z)
xlabel('X')
ylabel('Y')
zlabel('Z')
colormap hsv
```



ribbon

See Alsoplot, plot3, surface, waterfall"Polygons and Surfaces" on page 1-100 for related functions

rmappdata

Purpose	Remove application-defined data
Syntax	rmappdata(h,name)
Description	<pre>rmappdata(h,name) removes the application-defined data name from the object specified by handle h.</pre>
Remarks	Application data is data that is meaningful to or defined by your application which you attach to a figure or any GUI component (other than ActiveX controls) through its AppData property. Only Handle Graphics MATLAB objects use this property.
See Also	getappdata, isappdata, setappdata

rmdir

Purpose	Remove folder
Graphical Interface	As an alternative to the rmdir function, use the delete feature in the Current Folder browser.
Syntax	rmdir('folderName') rmdir('folderName',' s ') [status, message, messageid] = rmdir('folderName' ,'s ')
Description	<pre>rmdir('folderName') removes the folder folderName from the current folder, where folderName is empty. If folderName is not in the current folder, specify the relative path or the full path for folderName.</pre>
	<pre>rmdir('folderName', 's') removes the folder folderName and its contents from the current folder. With the 's' option, rmdir attempts to removes all subfolders and files in folderName regardless of their write permissions. The result for read-only files follows the practices of the operating system.</pre>
	[status, message, messageid] = rmdir('folderName','s') removes the folder folderName and its contents from the current folder, returning the status, a message, and the MATLAB message ID. Here, status is 1 for success and is 0 for error. message, messageid, and the s input argument are optional.
Remarks	When attempting to remove multiple folders, either by including a wildcard in the folder name or by specifying the 's' flag in rmdir, MATLAB produces an error if it is unable to remove all folders as expected. The error message lists the folder and files that MATLAB could not remove.
Examples	Remove Empty Folder
	Remove myfiles from the current folder, where myfiles is empty:
	<pre>rmdir('myfiles')</pre>

If the current folder is matlab/work, and myfiles is in d:/matlab/work/project/, use the relative path to remove myfiles:

```
rmdir('project/myfiles')
```

If the current folder is matlab/work, and myfiles is in d:/matlab/work/project/, use the full path to remove myfiles:

```
rmdir('d:/matlab/work/project/myfiles')
```

Remove Folder and All Contents

Remove myfiles, its subfolders, and all files in the folders, assuming myfiles is in the current folder:

```
rmdir('myfiles','s')
```

Remove Folder and Return Results

Remove myfiles from the current folder, where myfiles is not empty, and return the results:

[stat, mess, id]=rmdir('myfiles')

MATLAB returns:

```
stat =
    0
mess =
The directory is not empty.
id =
MATLAB:RMDIR:OSError
```

Remove myfiles and its contents using the s option, which is required for non-empty folders, and return the results:

```
[stat, mess]=rmdir('myfiles','s')
```

MATLAB returns: stat =
 1
mess =
 ''
See Also
catch, cd, copyfile, delete, dir, fileattrib, filebrowser,
MException, mkdir, movefile, try

"Managing Files in MATLAB"

Purpose	Remove directory on FTP server	
Syntax	rmdir(f,'dirname')	
Description	<pre>rmdir(f, 'dirname') removes the directory dirname from the current directory of the FTP server f, where f was created using ftp.</pre>	
Examples	Connect to server testsite, view the contents of testdir, and remove the directory newdir from the directory testdir.	
	<pre>test=ftp('ftp.testsite.com'); cd(test,'testdir'); dir(test) newdir dir(test,'newdir') rmdir(test,'newdir'); dir(test,'testdir')</pre>	

See Also cd (ftp), delete (ftp), dir (ftp), ftp, mkdir (ftp)

rmfield

Purpose	Remove fields from structure
Syntax	<pre>s = rmfield(s, 'fieldname') s = rmfield(s, fields)</pre>
Description	<pre>s = rmfield(s, 'fieldname') removes the specified field from the structure array s.</pre>
	<pre>s = rmfield(s, fields) removes more than one field at a time. fields is a character array of field names or cell array of strings.</pre>
See Also	fieldnames, setfield, getfield, isfield, orderfields, dynamic field names

Purpose	Remove folders from search path
GUI Alternatives	As an alternative to the rmpath function, use the Set Path dialog box.
Syntax	rmpath('folderName') rmpath folderName
Description	<pre>rmpath('folderName') removes the specified folder from the search path . Use the full path for folderName. pmpath folderName is the command form of the suntax</pre>
	rmpath folderName is the command form of the syntax.
Examples	Remove /usr/local/matlab/mytools from the search path: rmpath /usr/local/matlab/mytools
See Also	addpath, cd, dir, genpath, matlabroot, path, pathsep, pathtool, rehash, restoredefaultpath, savepath, userpath, what "Using the MATLAB Search Path"

<u>rmp</u>ref

Purpose	Remove preference
Syntax	rmpref('group','pref') rmpref('group',{'pref1','pref2','prefn'}) rmpref('group')
Description	<pre>rmpref('group', 'pref') removes the preference specified by group and pref. It is an error to remove a preference that does not exist.</pre>
	<pre>rmpref('group',{'pref1','pref2','prefn'}) removes each preference specified in the cell array of preference names. It is an error if any of the preferences do not exist.</pre>
	<pre>rmpref('group') removes all the preferences for the specified group. It is an error to remove a group that does not exist.</pre>
Examples	addpref('mytoolbox','version','1.0') rmpref('mytoolbox')
See Also	addpref, getpref, ispref, setpref, uigetpref, uisetpref

Purpose Root


Description The root is a graphics object that corresponds to the computer screen. There is only one root object and it has no parent. The children of the root object are figures.

The root object exists when you start MATLAB; you never have to create it and you cannot destroy it. Use set and get to access the root properties.

See Also diary, echo, figure, format, gcf, get, set

Root Properties for descriptions of all root object properties

Object Hierarchy



Root Properties

Purpose	Root properties
Modifying Properties	You can set and query graphics object properties in two ways:
	• Property Editor is an interactive tool that enables you to see and change object property values.
	• The set and get commands enable you to set and query the values of properties.
	To change the default values of properties, see "Setting Default Property Values".
Root Properties	This section lists property names along with the type of values each accepts. Curly braces {} enclose default values.
	BusyAction cancel {queue}
	Not used by the root object.
	ButtonDownFcn string
	Not used by the root object.
	CallbackObject handle (read only)
	<i>Handle of current callback's object</i> . This property contains the handle of the object whose callback routine is currently executing. If no callback routines are executing, this property contains the empty matrix []. See also the gco command.
	Children vector of handles
	Handles of child objects. A vector containing the handles of all nonhidden figure objects (see HandleVisibility for more

information). You can change the order of the handles and thereby change the stacking order of the figures on the display.

Clipping

{on} | off

Clipping has no effect on the root object.

CommandWindowSize

[columns rows]

Current size of command window. This property contains the size of the MATLAB command window in a two-element vector. The first element is the number of columns wide and the second element is the number of rows tall.

CreateFcn

The root does not use this property.

CurrentFigure

figure handle

Handle of the current figure window, which is the one most recently created, clicked in, or made current with the statement:

figure(h)

which restacks the figure to the top of the screen, or:

set(0, 'CurrentFigure',h)

which does not restack the figures. In these statements, h is the handle of an existing figure. If there are no figure objects:

get(0, 'CurrentFigure')

returns the empty matrix. Note, however, that gcf always returns a figure handle, and creates one if there are no figure objects.

DeleteFcn

string

This property is not used, because you cannot delete the root object.

Diary

on | {off}

Diary file mode. When this property is on, MATLAB maintains a file (whose name is specified by the DiaryFile property) that saves a copy of all keyboard input and most of the resulting output. See also the diary command.

DiaryFile

string

Diary filename. The name of the diary file. The default name is diary.

Echo

on | {off}

Script echoing mode. When Echo is on, MATLAB displays each line of a script file as it executes. See also the echo command.

ErrorMessage

string

Text of last error message. This property contains the last error message issued by MATLAB.

FixedWidthFontName

font name

Fixed-width font to use for axes, text, and uicontrols whose FontName is set to FixedWidth. MATLAB uses the font name specified for this property as the value for axes, text, and uicontrol FontName properties when their FontName property is set to FixedWidth. Specifying the font name with this property eliminates the need to hardcode font names in MATLAB applications and thereby enables these applications to run without modification in locales where non-ASCII character sets are required. In these cases, MATLAB attempts to set the value of FixedWidthFontName to the correct value for a given locale.

MATLAB application developers should not change this property, but should create axes, text, and uicontrols with FontName properties set to FixedWidth when they want to use a fixed-width font for these objects.

MATLAB end users can set this property if they do not want to use the preselected value. In locales where Latin-based characters are used, Courier is the default.

Format

```
short | {shortE} | long | longE | bank |
hex | + | rat
```

Output format mode. This property sets the format used to display numbers. See also the format command.

- short Fixed-point format with 5 digits
- shortE Floating-point format with 5 digits
- shortG Fixed- or floating-point format displaying as many significant figures as possible with 5 digits
- long Scaled fixed-point format with 15 digits
- longE Floating-point format with 15 digits
- longG Fixed- or floating-point format displaying as many significant figures as possible with 15 digits
- bank Fixed-format of dollars and cents
- hex Hexadecimal format
- + Displays + and symbols
- rat Approximation by ratio of small integers

FormatSpacing
 compact | {loose}

Output format spacing (see also format command).

- compact Suppress extra line feeds for more compact display.
- loose Display extra line feeds for a more readable display.

HandleVisibility

{on} | callback | off

This property is not useful on the root object.

HitTest

{on} | off

This property is not useful on the root object.

```
Interruptible
```

{on} | off

This property is not useful on the root object.

Language

string

System environment setting.

MonitorPositions

[x y width height;x y width height]

Width and height of primary and secondary monitors, in pixels. This property contains the width and height of each monitor connnected to your computer. The x and y values for the primary monitor are 0, 0 and the width and height of the monitor are specified in pixels.

The secondary monitor position is specified as:

x = primary monitor width + 1

```
y = primary monitor height + 1
```

Querying the value of the figure MonitorPositions on a multiheaded system returns the position for each monitor on a separate line.

```
v = get(0, 'MonitorPositions')
v =
x y width height % Primary monitor
x y width height % Secondary monitor
```

The value of the ScreenSize property is inconsistent when using multiple monitors. If you want specific and consistent values, use the MonitorPositions property.

Parent

handle

Handle of parent object. This property always contains the empty matrix, because the root object has no parent.

PointerLocation

[x,y]

Current location of pointer. A vector containing the *x*- and *y*-coordinates of the pointer position, measured from the lower left corner of the screen. You can move the pointer by changing the values of this property. The Units property determines the units of this measurement.

This property always contains the current pointer location, even if the pointer is not in a MATLAB window. A callback routine querying the PointerLocation can get a value different from the location of the pointer when the callback was triggered. This difference results from delays in callback execution caused by competition for system resources. On Macintosh platforms, you cannot change the pointer location using the set command.

PointerWindow

handle (read only)

Handle of window containing the pointer. MATLAB sets this property to the handle of the figure window containing the pointer. If the pointer is not in a MATLAB window, the value of this property is 0. A callback routine querying the PointerWindow can get the wrong window handle if you move the pointer to another window before the callback executes. This error results from delays in callback execution caused by competition for system resources.

RecursionLimit

integer

Number of nested MATLAB file calls. This property sets a limit to the number of nested calls to MATLAB files MATLAB will make before stopping (or potentially running out of memory). By default the value is set to a large value. Setting this property to a smaller value (something like 150, for example) should prevent MATLAB from running out of memory and will instead cause MATLAB to issue an error when it reaches the limit.

ScreenDepth

bits per pixel

Screen depth. The depth of the display bitmap (i.e., the number of bits per pixel). The maximum number of simultaneously displayed colors on the current graphics device is 2 raised to this power.

ScreenDepth supersedes the BlackAndWhite property. To override automatic hardware checking, set this property to 1. This value causes MATLAB to assume the display is monochrome. This is useful if MATLAB is running on color hardware but is being displayed on a monochrome terminal. Such a situation can cause MATLAB to determine erroneously that the display is color.

ScreenPixelsPerInch

Display resolution

DPI setting for your display. This property contains the setting of your display resolution specified in your system preferences.

ScreenSize

four-element rectangle vector (read only)

Screen size. A four-element vector:

[left,bottom,width,height]

that defines the display size. left and bottom are 0 for all Units except pixels, in which case left and bottom are 1. width and height are the screen dimensions in units specified by the Units property.

Determining Screen Size

Note that the screen size in absolute units (for example, inches) is determined by dividing the number of pixels in width and height by the screen DPI (see the ScreenPixelPerInch property). This value is approximate and might not represent the actual size of the screen.

Note that the ScreenSize property is static. Its values are read only at MATLAB startup and not updated if system display settings change. Also, the values returned might not represent the usable screen size for application developers due to the presence of other GUIs, such as the Microsoft Windows task bar.

Selected

on | off

This property has no effect on the root level.

```
SelectionHighlight
    {on} | off
```

This property has no effect on the root level.

ShowHiddenHandles

on | {off}

Show or hide handles marked as hidden. When set to on, this property disables handle hiding and exposes all object handles regardless of the setting of an object's HandleVisibility property. When set to off, all objects so marked remain hidden within the graphics hierarchy.

Тад

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. While it is not necessary to identify the root object with a tag (since its handle is always 0), you can use this property to store any string value that you can later retrieve using set.

Туре

string (read only)

Class of graphics object. For the root object, Type is always 'root'.

UIContextMenu handle

This property has no effect on the root level.

Units

```
{pixels} | normalized | inches | centimeters
| points | characters
```

Unit of measurement. This property specifies the units MATLAB uses to interpret size and location data. All units are measured from the lower left corner of the screen. Normalized units map the lower left corner of the screen to (0,0) and the upper right corner to (1.0,1.0). inches, centimeters, and points are absolute units (one point equals 1/72 of an inch). Characters are units defined by characters from the default system font; the width of one unit is the width of the letter x, the height of one character is the distance between the baselines of two lines of text.

This property affects the PointerLocation and ScreenSize properties. If you change the value of Units, it is good practice to return it to its default value after completing your operation, so as not to affect other functions that assume Units is set to the default value.

UserData

matrix

User-specified data. This property can be any data you want to associate with the root object. MATLAB does not use this property, but you can access it using the set and get functions.

Visible

{on} | off

Object visibility. This property has no effect on the root object.

See Also root object

roots

Purpose	Polynomial roots
Syntax	r = roots(c)
Description	r = roots(c) returns a column vector whose elements are the roots of the polynomial c.
	Row vector c contains the coefficients of a polynomial, ordered in descending powers. If c has n+1 components, the polynomial it represents is $c_1s^n + \ldots + c_ns + c_{n+1}$.
Remarks	Note the relationship of this function to $p = poly(r)$, which returns a row vector whose elements are the coefficients of the polynomial. For vectors, roots and poly are inverse functions of each other, up to ordering, scaling, and roundoff error.
Examples	The polynomial $s^3 - 6s^2 - 72s - 27$ is represented in MATLAB software as p = [1 -6 -72 -27]
	The roots of this polynomial are returned in a column vector by r = roots(p) r = 12.1229 -5.7345 -0.3884
Algorithm	<pre>The algorithm simply involves computing the eigenvalues of the companion matrix: A = diag(ones(n-1,1),-1); A(1,:) = -c(2:n+1)./c(1); cir(A)</pre>

eig(A)

It is possible to prove that the results produced are the exact eigenvalues of a matrix within roundoff error of the companion matrix A, but this does not mean that they are the exact roots of a polynomial with coefficients within roundoff error of those in c.

See Also fzero, poly, residue

Purpose

Angle histogram plot



GUI Alternatives

To graph selected variables, use the Plot Selector **Plot(t,y)** in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in *plot edit* mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.

Syntax

rose(theta)
rose(theta,x)
rose(theta,nbins)
rose(axes_handle,...)
h = rose(...)
[tout,rout] = rose(...)

Description


rose(theta) creates an angle histogram, which is a polar plot showing the distribution of values grouped according to their numeric range, showing the distribution of theta in 20 angle bins or less. The vector theta, expressed in radians, determines the angle of each bin from the origin. The length of each bin reflects the number of elements in theta that fall within a group, which ranges from 0 to the greatest number of elements deposited in any one bin.

rose(theta,x) uses the vector x to specify the number and the locations of bins. length(x) is the number of bins and the values of x specify the center angle of each bin. For example, if x is a five-element vector, rose distributes the elements of theta in five bins centered at the specified x values.

<code>rose(theta,nbins)</code> plots <code>nbins</code> equally spaced bins in the range [0, 2*pi]. The default is 20.

rose(axes_handle,...) plots into the axes with handle axes_handle
instead of the current axes (gca).
h = rose(...) returns the handles of the line objects used to create
the graph.
[tout,rout] = rose(...) returns the vectors tout and rout so
polar(tout,rout) generates the histogram for the data. This syntax
does not generate a plot.
Example
Create a rose plot showing the distribution of 50 random numbers.
theta = 2*pi*rand(1,50);
rose(theta)

rose



See Also compass, feather, hist, line, polar "Histograms" on page 1-100 for related functions Histograms in Polar Coordinates for another example

Purpose	Classic sym	metric	eigenv	alue tes	st probl	em			
Syntax	A = rossei	•							
Description	A = rosser returns the Rosser matrix. This matrix was a challenge for many matrix eigenvalue algorithms. But LAPACK's DSYEV routine used in MATLAB software has no trouble with it. The matrix is 8-by-8 with integer elements. It has:								
	• A double	eigenv	alue						
	• Three ne	arly eq	ual eig	envalue	es				
	• Dominar	nt eigen	values	of oppo	site sig	n			
	• A zero ei	genvalı	1e						
	• A small,	0		value					
Examples	rosser		0						
	ans =								
	611	196	- 192	407	- 8	- 52	- 49	29	
	196	899	113	-192	-71	- 43	- 8	-44	
	- 192	113	899	196	61	49	8	52	
	407	-192	196	611	8	44	59	-23	
	-8	-71	61	8	411	- 599	208	208	
	-52	- 43	49	44	- 599	411	208	208	
	- 49	- 8	8	59	208	208	99	-911	
	29	- 44	52	-23	208	208	-911	99	

Purpose	Rotate matrix 90 degrees
Syntax	B = rot90(A) B = rot90(A,k)
Description	B = rot90(A) rotates matrix A counterclockwise by 90 degrees. B = rot90(A,k) rotates matrix A counterclockwise by k*90 degrees, where k is an integer.
Examples	The matrix X = 1 2 3 4 5 6 7 8 9
	rotated by 90 degrees is Y = rot90(X) Y = 3 6 9 2 5 8 1 4 7
See Also	flipdim, fliplr, flipud

Purpose	Rotate object in specified direction
---------	--------------------------------------

Syntax rotate(h,direction,alpha) rotate(...,origin)


Description The rotate function rotates a graphics object in three-dimensional space, according to the right-hand rule.

rotate(h,direction,alpha) rotates the graphics object h by alpha degrees. direction is a two- or three-element vector that describes the axis of rotation in conjunction with the origin.


rotate(...,origin) specifies the origin of the axis of rotation as a three-element vector. The default origin is the center of the plot box.

Remarks The graphics object you want rotated must be a child of the same axes. The object's data is modified by the rotation transformation. This is in contrast to view and rotate3d, which only modify the viewpoint.

The axis of rotation is defined by an origin and a point P relative to the origin. P is expressed as the spherical coordinates [theta phi] or as Cartesian coordinates.



The two-element form for direction specifies the axis direction using the spherical coordinates [theta phi]. theta is the angle in the x-y plane counterclockwise from the positive x-axis. phi is the elevation of the direction vector from the x-y plane.



The three-element form for direction specifies the axis direction using Cartesian coordinates. The direction vector is the vector from the origin to (X,Y,Z).

Examples Rotate a graphics object 180° about the *x*-axis.

h = surf(peaks(20));
rotate(h,[1 0 0],180)

Rotate a surface graphics object 45° about its center in the z direction.

```
h = surf(peaks(20));
zdir = [0 0 1];
center = [10 10 0];
rotate(h,zdir,45,center)
```

Remarks	rotate changes the Xdata, Ydata, and Zdata properties of the appropriate graphics object.
See Also	rotate3d, sph2cart, view
	The axes CameraPosition, CameraTarget, CameraUpVector, CameraViewAngle
	"Object Manipulation" on page 1-110 for related functions

rotate3d

Purpose	Rotate 3-D view using mouse
GUI Alternatives	Use the Rotate3D tool on the figure toolbar to enable and disable rotate3D mode on a plot, or select Rotate 3D from the figure's Tools menu. For details, see "Rotate 3D — Interactive Rotation of 3-D Views" in the MATLAB Graphics documentation.
Syntax	<pre>rotate3d on rotate3d off rotate3d rotate3d rotate3d(figure_handle,) rotate3d(axes_handle,) h = rotate3d(figure_handle)</pre>
Description	<pre>rotate3d on enables mouse-base rotation on all axes within the current figure. rotate3d off disables interactive axes rotation in the current figure. rotate3d toggles interactive axes rotation in the current figure. rotate3d(figure_handle,) enables rotation within the specified figure instead of the current figure. rotate3d(axes_handle,) enables rotation only in the specified axes. h = rotate3d(figure_handle) returns a rotate3d mode object for figure figure_handle for you to customize the mode's behavior.</pre>
	• FigureHandle <handle> — The associated figure handle, a read-only property that cannot be set</handle>

• *Enable* 'on'|'off' — Specifies whether this figure mode is currently enabled on the figure

• RotateStyle 'orbit'|'box' — Sets the method of rotation

'orbit' rotates the entire axes; 'box' rotates a plot-box outline of the axes.

Rotate3D Mode Callbacks

You can program the following callbacks for rotate3d mode operations.

• ButtonDownFilter <function_handle> — Function to intercept ButtonDown events

The application can inhibit the rotate operation under circumstances the programmer defines, depending on what the callback returns. The input function handle should reference a function with two implicit arguments (similar to handle callbacks):

ActionPreCallback <function_handle> — Function to execute before rotating

Set this callback to listen to when a rotate operation will start. The input function handle should reference a function with two implicit arguments (similar to Handle Graphics object callbacks):

function myfunction(obj,event_obj)
% obj handle to the figure that has been clicked on
% event_obj object containing struct of event data

The event data has the following field:

Axes The handle of the axes that is being panned

• ActionPostCallback <function_handle> — Function to execute after rotating

Set this callback to listen to when a rotate operation has finished. The input function handle should reference a function with two implicit arguments (similar to Handle Graphics object callbacks):

```
function myfunction(obj,event_obj)
% obj handle to the figure that has been clicked on
% event_obj object containing struct of event data (same as the
% event data of the 'ActionPreCallback' callback)
```

Rotate3D Mode Utility Functions

The following functions in pan mode query and set certain of its properties.

• flags = isAllowAxesRotate(h,axes) — Function querying permission to rotate axes

Calling the function isAllowAxesRotate on the rotate3d object, h, with a vector of axes handles, axes, as input will return a logical array of the same dimension as the axes handle vector which indicate whether a rotate operation is permitted on the axes objects.

• setAllowAxesRotate(h,axes,flag) — Function to set permission to pan axes

Calling the function setAllowAxesRotate on the rotate3d object, h, with a vector of axes handles, axes, and a logical scalar, flag, will either allow or disallow a rotate operation on the axes objects.

Examples Example 1

Simple 3-D rotation

```
surf(peaks);
rotate3d on
% rotate the plot using the mouse pointer.
```

Example 2

Rotate the plot using the "Plot Box" rotate style:

```
surf(peaks);
h = rotate3d;
set(h,'RotateStyle','box','Enable','on');
% Rotate the plot.
```

Example 3

Create two axes as subplots and then prevent one from rotating:

```
ax1 = subplot(1,2,1);
surf(peaks);
h = rotate3d;
ax2 = subplot(1,2,2);
surf(membrane);
setAllowAxesRotate(h,ax2,false);
% rotate the plots.
```

Example 4

Create a buttonDown callback for rotate mode objects to trigger. Copy the following code to a new file, execute it, and observe rotation behavior:

```
function demo_mbd
% Allow a line to have its own 'ButtonDownFcn' callback.
hLine = plot(rand(1,10));
set(hLine,'ButtonDownFcn','disp(''This executes'')');
set(hLine,'Tag','DoNotIgnore');
h = rotate3d;
set(h,'ButtonDownFilter',@mycallback);
set(h,'Enable','on');
% mouse-click on the line
%
```

```
function [flag] = mycallback(obj,event_obj)
% If the tag of the object is 'DoNotIgnore', then return true.
objTag = get(obj,'Tag');
if strcmpi(objTag,'DoNotIgnore')
    flag = true;
else
    flag = false;
end
```

Example 5

Create callbacks for pre- and post-buttonDown events for rotate3D mode objects to trigger. Copy the following code to a new file, execute it, and observe rotation behavior:

```
function demo_mbd2
% Listen to rotate events
surf(peaks);
h = rotate3d;
set(h,'ActionPreCallback',@myprecallback);
set(h,'ActionPostCallback',@mypostcallback);
set(h,'Enable','on');
%
function myprecallback(obj,evd)
disp('A rotation is about to occur.');
%
function mypostcallback(obj,evd)
newView = round(get(evd.Axes,'View'));
msgbox(sprintf('The new view is [%d %d].',newView));
```

Remarks When enabled, rotate3d provides continuous rotation of axes and the objects it contains through mouse movement. A numeric readout appears in the lower left corner of the figure during rotation, showing the current azimuth and elevation of the axes. Releasing the mouse button removes the animated box and the readout. This differs from the camorbit function in that while the rotate3d tool modifies the View property of the axes, the camorbit function fixes the aspect ratio

and modifies the CameraTarget, CameraPosition and CameraUpVector properties of the axes. See Axes Properties for more information.

You can also enable 3-D rotation from the figure **Tools** menu or the figure toolbar.

You can create a rotate3D mode object once and use it to customize the behavior of different axes, as example 3 illustrates. You can also change its callback functions on the fly.

Note Do not change figure callbacks within an interactive mode. While a mode is active (when panning, zooming, etc.), you will receive a warning if you attempt to change any of the figure's callbacks and the operation will not succeed. The one exception to this rule is the figure WindowButtonMotionFcn callback, which can be changed from within a mode. Therefore, if you are creating a GUI that updates a figure's callbacks, the GUI should some keep track of which interactive mode is active, if any, before attempting to do this.

When you assign different 3-D rotation behaviors to different subplot axes via a mode object and then link them using the linkaxes function, the behavior of the axes you manipulate with the mouse will carry over to the linked axes, regardless of the behavior you previously set for the other axes.

See Also camorbit, pan, rotate, view, zoom Object Manipulation for related functions Axes Properties for related properties

round

Purpose	Round to nearest integ	ger		
Syntax	Y = round(X)			
Description	Y = round(X) rounds complex X, the imagina			-
Examples	a = [-1.9, -0.2, 3.4,	5.6, 7.0, 2.4+3.6i]	
	a = Columns 1 through 4 -1.9000 Columns 5 through 6 7.0000 round(a)	-0.2000	3.4000	5.6000
	ans = Columns 1 through 4 -2.0000 Columns 5 through 6 7.0000	0	3.0000	6.0000

See Also ceil, fix, floor

Purpose	Reduced row echelon form			
Syntax	R = rref(A) [R,jb] = rref(A) [R,jb] = rref(A,tol)			
Description	<pre>R = rref(A) produces the reduced row echelon form of A using Gauss Jordan elimination with partial pivoting. A default tolerance of (max(size(A))*eps *norm(A,inf)) tests for negligible column elements.</pre>			
	[R,jb] = rref(A) also returns a vector jb such that:			
	• r = length(jb) is this algorithm's idea of the rank of A.			
	• $x(jb)$ are the pivot variables in a linear system $Ax = b$.			
	• A(:,jb) is a basis for the range of A.			
	• R(1:r,jb) is the r-by-r identity matrix.			
	[R,jb] = rref(A,tol) uses the given tolerance in the rank tests.			
	Roundoff errors may cause this algorithm to compute a different value for the rank than rank, orth and null.			
Examples	Use rref on a rank-deficient magic square:			
	A = magic(4), R = rref(A)			
	$A = \begin{bmatrix} 16 & 2 & 3 & 13 \\ 5 & 11 & 10 & 8 \\ 9 & 7 & 6 & 12 \\ 4 & 14 & 15 & 1 \end{bmatrix}$			
	R = 1 0 0 1			
	0 1 0 3			

0	0	1	- 3
0	0	0	0

See Also

inv, lu, rank

Purpose	Convert real Schur form to complex Schur form			
Syntax	[U,T] = rsf2csf(U,T)			
Description	The <i>complex Schur form</i> of a matrix is upper triangular with the eigenvalues of the matrix on the diagonal. The <i>real Schur form</i> has the real eigenvalues on the diagonal and the complex eigenvalues in 2-by-2 blocks on the diagonal.			
	[U,T] = rsf2csf(U,T) converts the real Schur form to the complex form.			
	Arguments U and T represent the unitary and Schur forms of a matrix A, respectively, that satisfy the relationships: $A = U^*T^*U'$ and $U'^*U = eye(size(A))$. See schur for details.			
Examples	Given matrix A,			
	1 1 1 3 1 2 1 1 1 1 3 1 -2 1 1 4			
	with the eigenvalues			
	4.8121 1.9202 + 1.4742i 1.9202 + 1.4742i 1.3474			
	Generating the Schur form of A and converting to the complex Schur form			
	[u,t] = schur(A); [U,T] = rsf2csf(u,t)			
	yields a triangular matrix T whose diagonal (underlined here for readability) consists of the eigenvalues of A.			

U =

-0.4916	-0.2756 - 0.4411i	0.2133 + 0.5699i	-0.3428
-0.4980	-0.1012 + 0.2163i	-0.1046 + 0.2093i	0.8001
-0.6751	0.1842 + 0.3860i	-0.1867 - 0.3808i	-0.4260
-0.2337	0.2635 - 0.6481i	0.3134 - 0.5448i	0.2466
T =			
4.8121	-0.9697 + 1.0778i	-0.5212 + 2.0051i	-1.0067
0	1.9202 + 1.4742i	2.3355	0.1117 + 1.6547i
0	0	1.9202 - 1.4742i	0.8002 + 0.2310i
0	0	0	1.3474

See Also

schur

Purpose	Run script that is not on current path
Syntax	run scriptname
Description	run scriptname runs the MATLAB script specified by scriptname. If scriptname contains the full pathname to the script file, then run changes the current folder to be the one in which the script file resides, executes the script, and sets the current folder back to what it was. The script is run within the caller's workspace.
	run is a convenience function that runs scripts that are not currently on the path. Typically, you just type the name of a script at the MATLAB prompt to execute it. This works when the script is on your path. Use the cd or addpath function to make a script executable by entering the script name alone.
See Also	cd, addpath

save

Purpose	Save workspace variables to file
Syntax	<pre>save(filename) save(filename, variables) save(filename, '-struct', structName, fieldNames) save(filename,, '-append') save(filename,, format) save(filename,, version) save filename</pre>
Description	<pre>save(filename) stores all variables from the current workspace in a MATLAB formatted binary file (MAT-file) called filename.</pre>
	save(filename, variables) stores only the specified variables.
	<pre>save(filename, '-struct', structName, fieldNames) stores the fields of the specified scalar structure as individual variables in the file. If you include the optional fieldNames, the save function stores only the specified fields of the structure. You cannot specify variables and the '-struct' keyword in the same call to save.</pre>
	<pre>save(filename,, '-append') adds new variables to an existing file. You can specify the '-append' option with additional inputs such as variables, '-struct', format, or version.</pre>
	<pre>save(filename,, format) saves in the specified format: '-mat' or '-ascii'. You can specify the format option with additional inputs such as variables, '-struct', '-append', or version.</pre>
	<pre>save(filename,, version) saves to MAT-files in the specified version: '-v4', '-v6', '-v7', or '-v7.3'. You can specify the version option with additional inputs such as variables, '-struct', '-append', or format.</pre>
	save filename is the command form of the syntax, for convenient

nt saving from the command line. With command syntax, you do not need to enclose input strings in single quotation marks. Separate inputs with spaces instead of commas. Do not use command syntax if inputs such as filename are variables. For more information, see "Command

vs. Function Syntax" in the MATLAB Programming Fundamentals documentation.

Input Arguments	filename Name of a file. If you do not specify <i>filename</i> , the save function
	saves to a file named matlab.mat.
	If <i>filename</i> does not include an extension and the value of <i>format</i> is -mat (the default), MATLAB appends .mat. If <i>filename</i> does not include a full path, MATLAB saves in the current folder. You must have permission to write to the file.
	Default: 'matlab.mat'

variables

Description of the variables to save. Use one of the following forms:

var1, var2,	Save the listed variables. Use the '*' wildcard to match patterns. For example, save('A*') saves all variables that start with A.
'-regexp', <i>expressions</i>	Save only the variables that match the specified regular expressions. MATLAB treats all inputs as regular expressions, except the optional <i>filename</i> . The <i>filename</i> must appear immediately after the save command.

Default: all variables

'-struct'

Keyword to request saving the fields of a scalar structure as individual variables in the file. The *structName* input must appear immediately after the *-struct* keyword.

structName

Name of a scalar structure. Required when you use the '-struct' keyword.

fieldNames

Description of the fields of a structure to save as individual variables in the file. Use the same forms listed for *variables*. If you use the '-regexp' keyword, MATLAB treats all inputs as regular expressions except *filename* and *structName*.

'-append'

Keyword to add data to an existing file. For MAT-files, -append adds new variables to the file or replaces the saved values of existing variables with values in the workspace. For ASCII files, -append adds data to the end of the file.

format

Specifies the format of the file, regardless of any specified extension. Use one of the following combinations (not case sensitive):

'-mat'	Binary MAT-file format (default).
'-ascii'	8-digit ASCII format.
'-ascii', '-tabs'	Tab-delimited 8-digit ASCII format.
'-ascii', '-double'	16-digit ASCII format.
'-ascii', '-double', '-tabs'	Tab-delimited 16-digit ASCII format.

For MAT-files, data saved on one machine and loaded on another machine retains as much accuracy and range as the different machine floating-point formats allow.

For ASCII file formats, the save function has the following limitations:

- Each variable must be a two-dimensional double or character array.
- MATLAB translates characters to their corresponding internal ASCII codes. For example, 'abc' appears in an ASCII file as:

9.7000000e+001 9.8000000e+001 9.9000000e+001

- The output includes only the real component of complex numbers.
- MATLAB writes data from each variable sequentially to the file. If you plan to use the load function to read the file, all variables must have the same number of columns. The load function creates a single variable from the file.

For more flexibility in creating ASCII files, use ${\tt dlmwrite}\ {\tt or}\ {\tt fprintf}.$

version

Specifies the version of the file. Applies to MAT-files only.

The following table shows the available MAT-file version options and the corresponding supported features.

Option	Can Load in Versions	Supported Features
'-v7.3'	7.3 or later	Version 7.0 features plus support for data items greater than or equal to 2 GB on 64-bit systems.
' - v7 '	7.0 or later	Version 6 features plus data compression and Unicode character encoding. Unicode encoding enables file sharing between systems that use different default character encoding schemes.
'-v6'	5 or later	Version 4 features plus <i>N</i> -dimensional arrays, cell arrays and structures, and variable names greater than 19 characters.
' - v4 '	all	Two-dimensional double, character, and sparse arrays.

If any data items require features that the specified version does not support, MATLAB does not save those items and issues a warning. You cannot specify a version later than your version of MATLAB software.

To view or set the default version for MAT-files, select **File > Preferences > General > MAT-Files**.

Examples Save all variables from the workspace in binary MAT-file test.mat. Remove the variables from the workspace, and retrieve the data with the load function.

save test.mat clear load test.mat Create a variable savefile that stores the name of a file, pqfile.mat. Save two variables to the file.

```
savefile = 'pqfile.mat';
p = rand(1, 10);
q = ones(10);
save(savefile, 'p', 'q')
```

Save data to an ASCII file, and view the contents of the file with the type function:

```
p = rand(1, 10);
q = ones(10);
save('pqfile.txt', 'p', 'q', '-ASCII')
type pqfile.txt
```

Alternatively, use command syntax for the save operation:

save pqfile.txt p q -ASCII

Save the fields of structure s1 as individual variables. Check the contents of the file with the whos function. Clear the workspace and load the contents of a single field.

```
s1.a = 12.7;
s1.b = {'abc', [4 5; 6 7]};
s1.c = 'Hello!';
save('newstruct.mat', '-struct', 's1');
disp('Contents of newstruct.mat:')
whos('-file', 'newstruct.mat')
clear('s1')
load('newstruct.mat', 'b')
```

save

	Save any variables in the workspace with names that begin with Mon, Tue, or Wed to mydata.mat:
	<pre>save('mydata', '-regexp', '^Mon ^Tue ^Wed');</pre>
Alternatives	To save data from the MATLAB desktop, select File > Save Workspace As , or use the Workspace browser.
See Also	clear hgsave fileformats load regexp saveas whos workspace
How To	• "Exporting to MAT-Files"
	 "Exporting to Text Data Files"

Purpose	Serialize control object to file
Syntax	h.save('filename') save(h, 'filename')
Description	h.save('filename') saves the COM control object, h, to the file specified in the string, filename.
	<pre>save(h, 'filename') is an alternate syntax for the same operation.</pre>
	Note The COM save function is only supported for controls at this time.
Remarks	COM functions are available on Microsoft Windows systems only.
Examples	Create an mwsamp control and save its original state to the file mwsample:
	<pre>f = figure('position', [100 200 200 200]); h = actxcontrol('mwsamp.mwsampctrl.2', [0 0 200 200], f); h.save('mwsample')</pre>
	Now, alter the figure by changing its label and the radius of the circle:
	h.Label = 'Circle'; h.Radius = 50; h.Redraw;
	Using the load function, you can restore the control to its original state:
	h.load('mwsample'); h.get
	MATLAB displays the original values:
	ans = Label: 'Label' Radius: 20

See Also load (COM), actxcontrol, actxserver, release, delete (COM)

Purpose	Save serial port objects and variables to file
Syntax	save filename save filename obj1 obj2
Description	save filename saves all MATLAB variables to the file filename. If an extension is not specified for filename, then the .mat extension is used.
	save filename obj1 obj2 saves the serial port objects obj1 obj2 to the file filename.
Remarks	You can use save in the functional form as well as the command form shown above. When using the functional form, you must specify the filename and serial port objects as strings. For example. to save the serial port object s to the file MySerial.mat on a Windows platform
	s = serial('COM1'); save('MySerial','s')
	Any data that is associated with the serial port object is not automatically stored in the file. For example, suppose there is data in the input buffer for obj. To save that data to a file, you must bring it into the MATLAB workspace using one of the synchronous read functions, and then save to the file using a separate variable name. You can also save data to a text file with the record function.
	You return objects and variables to the MATLAB workspace with the load command. Values for read-only properties are restored to their default values upon loading. For example, the Status property is restored to closed. To determine if a property is read-only, examine its reference pages.
Example	This example illustrates how to use the command and functional form of save on a Windows platform.
	s = serial('COM1'); set(s,'BaudRate',2400,'StopBits',1) save MySerial1 s

```
set(s,'BytesAvailableFcn',@mycallback)
save('MySerial2','s')
```

See Also Functions

load, record

Properties

Status

Purpose	Save figure or Simulink block diagram using specified format
GUI Alternative	Use File > Save As on the figure window menu to access the Save As dialog, in which you can select a graphics format. For details, see "Exporting in a Specific Graphics Format" in the MATLAB Graphics documentation. Sizes of files written to image formats by this GUI and by saveas can differ due to disparate resolution settings.
Syntax	saveas(h,'filename.ext') saveas(h,'filename','format')
Description	<pre>saveas(h, 'filename.ext') saves the figure or Simulink block diagram with the handle h to the file filename.ext. The format of the file is determined by the extension, ext. Allowable values for ext are listed in this table.</pre>
	You can need the headle of our Handle Counting shires to cover

You can pass the handle of any Handle Graphics object to saveas, which then saves the parent figure to the object you specified should h not be a figure handle. This means that saveas cannot save a subplot without also saving all subplots in its parent figure.

ext Value	Format
ai	Adobe® Illustrator '88
bmp	Windows bitmap
emf	Enhanced metafile
eps	EPS Level 1
fig	MATLAB figure (invalid for Simulink block diagrams)
jpg	JPEG image (invalid for Simulink block diagrams)
m	MATLAB file (invalid for Simulink block diagrams)
pbm	Portable bitmap

ext Value	Format
рсх	Paintbrush 24-bit
pdf	Portable Document Format
pgm	Portable Graymap
png	Portable Network Graphics
ppm	Portable Pixmap
tif	TIFF image, compressed

saveas(h, 'filename', 'format') saves the figure or Simulink block diagram with the handle h to the file called filename using the specified format. The filename can have an extension, but the extension is not used to define the file format. If no extension is specified, the standard extension corresponding to the specified format is automatically appended to the filename.

Allowable values for format are the extensions in the table above and the device drivers and graphic formats supported by print. The drivers and graphic formats supported by print include additional file formats not listed in the table above. When using a print device type to specify format for saveas, do not prefix it with -d.

Remarks You can use open to open files saved using saveas with an m or fig extension. Other saveas and print formats are not supported by open. Both the Save As and Export Setup dialog boxes that you access from a figure's File menu use saveas with the format argument, and support all device and file types listed above.

Note Whenever you specify a format for saving a figure with the **Save As** menu item , that file format is used again the next time you save that figure or a new one. If you do not want to save in the previously-used format, use **Save As** and be sure to set the **Save as type** drop-down menu to the kind of file you want to write. However, saving a figure with the **saveas** function and a format does not change the **Save as type** setting in the GUI.

If you want to control the size or resolution of figures saved in image (bit-mapped) formats, such as BMP or JPG, use the print command and specify dots-per-inch resolution with the r switch.

Examples Example 1: Specify File Extension

Save the current figure that you annotated using the Plot Editor to a file named pred_prey using the MATLAB fig format. This allows you to open the file pred_prey.fig at a later time and continue editing it with the Plot Editor.

```
saveas(gcf,'pred_prey.fig')
```

Example 2: Specify File Format but No Extension

Save the current figure, using Adobe Illustrator format, to the file logo. Use the ai extension from the above table to specify the format. The file created is logo.ai.

```
saveas(gcf,'logo', 'ai')
```

This is the same as using the Adobe Illustrator format from the print devices table, which is -dill; use doc print or help print to see the table for print device types. The file created is logo.ai. MATLAB automatically appends the ai extension for an Illustrator format file because no extension was specified.

```
saveas(gcf,'logo', 'ill')
```

Example 3: Specify File Format and Extension

Save the current figure to the file star.eps using the Level 2 Color PostScript format. If you use doc print or help print, you can see from the table for print device types that the device type for this format is -dpsc2. The file created is star.eps.

saveas(gcf,'star.eps', 'psc2')

In another example, save the current Simulink block diagram to the file trans.tiff using the TIFF format with no compression. From the table for print device types, you can see that the device type for this format is -dtiffn. The file created is trans.tiff.

saveas(gcf,'trans.tiff', 'tiffn')

See Also hgsave, open, print "Printing" on page 1-102 for related functions Simulink users, see also save_system

Purpose	Modify save process for object
Syntax	b = saveobj(a)
Description	b = saveobj(a) is called by the save function if the class of a defines a saveobj method. save writes the returned value, b, to the MAT-file.
	Define a loadobj method to take the appropriate action when loading the object.
	If A is an array of objects, MATLAB invokes saveobj separately for each object saved.
Examples	Call the superclass saveobj method from the subclass implementation of saveobj with the following syntax:
	<pre>classdef mySub < super methods function sobj = saveobj(obj)</pre>
	end
	end
	end

See "Saving and Loading Objects from Class Hierarchies".

Update object when saved:

	end b = a; end
	See "Example — Maintaining Class Compatibility".
See Also	save load loadobj
Tutorials	• "Saving and Loading Objects"

Purpose	Save current search path
GUI Alternatives	As an alternative to the savepath function, use the Set Path dialog box.
Syntax	savepath savepath folderName/ pathdef.m status = savepath
Description	savepath saves the current MATLAB search path for use in a future session. savepath saves the search path to the pathdef.m file that MATLAB located at startup, or to the current folder if a pathdef.m file exists there. To save the search path programmatically each time you exit MATLAB, use savepath in a finish.m file.
	<pre>savepath folderName/pathdef.m saves the current search path to pathdef.m located in folderName. Use this form of the syntax if you do not have write access to the current pathdef.m. If you do not specify folderName, MATLAB saves pathdef.m in the current folder. folderName can be a relative or absolute path. To use the saved search path automatically in a future session, make folderName be the startup folder for MATLAB.</pre>
	<pre>status = savepath returns 0 when savepath was successful and 1 when savepath failed.</pre>
Examples	Save the current search path to pathdef.m, located in I:/my_matlab_files:
	<pre>savepath I:/my_matlab_files/pathdef.m</pre>
See Also	addpath, cd, dir, finish, genpath, matlabroot, pathsep, pathtool, rehash, restoredefaultpath, rmpath, startup, userpath, what
	Topics in the User Guide:
	• "Running a Script When Quitting the MATLAB Program".

• "Using the MATLAB Search Path"


PurposeScatter plot



GUI Alternatives	To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.
Syntax	<pre>scatter(X,Y,S,C) scatter(X,Y) scatter(X,Y,S) scatter(,markertype) scatter(,'filled') scatter(,'PropertyName',propertyvalue) scatter(axes_handle,) h = scatter()</pre>
Description	scatter(X,Y,S,C) displays colored circles at the locations specified by the vectors X and Y (which must be the same size).
	S determines the area of each marker (specified in points^2). S can be a vector the same length as X and Y or a scalar. If S is a scalar, MATLAB draws all the markers the same size. If S is empty, the default size is used.
	C determines the color of each marker. When C is a vector the same length as X and Y, the values in C are linearly mapped to the colors in the current colormap. When C is a 1-by-3 matrix, it specifies the colors of the markers as RGB values. If you have 3 points in the scatter plot and wish to have the colors be indices into the colormap, C should be a 3-by-1 matrix. C can also be a color string (see ColorSpec for a list of color string specifiers).

scatter(X,Y) draws the markers in the default size and color.
<pre>scatter(X,Y,S) draws the markers at the specified sizes (S) with a single color. This type of graph is also known as a bubble plot.</pre>
<pre>scatter(,markertype) uses the marker type specified instead of 'o' (see LineSpec for a list of marker specifiers).</pre>
<pre>scatter(,'filled') fills the markers.</pre>
<pre>scatter(, 'PropertyName', propertyvalue) creates the scatter graph, applying the specified property settings. See scattergroup properties for a description of properties.</pre>
<pre>scatter(axes_handle,) plots into the axes object with handle axes_handle instead of the current axes object (gca).</pre>
<pre>h = scatter() returns the handle of the scattergroup object created.</pre>

Example load seamount scatter(x,y,5,z)



See Alsoscatter3, plot3"Scatter/Bubble Plots" on page 1-101 for related functionsSee Scattergroup Properties for property descriptions.

2 - 3425

scatter3

Purpose	3-D scatter plot
GUI Alternatives	To graph selected variables, use the Plot Selector For the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.
Syntax	<pre>scatter3(X,Y,Z,S,C) scatter3(X,Y,Z) scatter3(X,Y,Z,S) scatter3(,markertype) scatter3(,'filled') scatter3(,'PropertyName',propertyvalue) h = scatter3()</pre>
Description	scatter3(X,Y,Z,S,C) displays colored circles at the locations specified by the vectors X, Y, and Z (which must all be the same size).
	S determines the size of each marker (specified in points). S can be a vector the same length as X, Y, and Z or a scalar. If S is a scalar, MATLAB draws all the markers the same size.
	C determines the color of each marker. When C is a vector the same length as X and Y, the values in C are linearly mapped to the colors in the current colormap. When C is a 1-by-3 matrix, it specifies the colors of the markers as RGB values. If you have 3 points in the scatter plot and wish to have the colors be indices into the colormap, C should be a 3-by-1 matrix. C can also be a color string (see ColorSpec for a list of color string specifiers).
	scatter3(X,Y,Z) draws the markers in the default size and color.

scatter3(X,Y,Z,S) draws markers at the specified sizes (S) in a single color.

scatter3(...,markertype) uses the marker type specified instead of 'o' (see LineSpec for a list of marker specifiers).

scatter3(..., 'filled') fills the markers.


scatter3(..., 'PropertyName', propertyvalue) creates the scatter
graph, applying the specified property settings. See scattergroup
properties for a description of properties.


h = scatter3(...) returns handles to the scattergroup objects created by scatter3. See Scattergroup Properties for property descriptions.

Use plot3 for single color, single marker size 3-D scatter plots.

Examples

```
[x,y,z] = sphere(16);
X = [x(:)*.5 x(:)*.75 x(:)];
Y = [y(:)*.5 y(:)*.75 y(:)];
Z = [z(:)*.5 z(:)*.75 z(:)];
S = repmat([1 .75 .5]*10,prod(size(x)),1);
C = repmat([1 2 3],prod(size(x)),1);
scatter3(X(:),Y(:),Z(:),S(:),C(:),'filled'), view(-60,60)
```





Purpose	Define scattergroup properties	
Modifying Properties	You can set and query graphics object properties using the set and get commands or the Property Editor (propertyeditor).	
-	Note that you cannot define default property values for scattergroup objects.	
	See Plot Objects for information on scattergroup objects.	
Scattergroup Property Descriptions	This section provides a description of properties. Curly braces $\{\}$ enclose default values.	
	Annotation hg.Annotation object Read Only	
	Control the display of scattergroup objects in legends. The Annotation property enables you to specify whether this scattergroup object is represented in a figure legend.	
	Querying the Annotation property returns the handle of an hg.Annotation object. The hg.Annotation object has a property called LegendInformation, which contains an hg.LegendEntry object.	
	Once you have obtained the hg.LegendEntry object, you can set its IconDisplayStyle property to control whether the scattergroup object is displayed in a figure legend:	

IconDisplayStyle Value	Purpose
on	Include the scattergroup object in a legend as one entry, but not its children objects
off	Do not include the scattergroup or its children in a legend (default)
children	Include only the children of the scattergroup as separate entries in the legend

Setting the IconDisplayStyle Property

These commands set the IconDisplayStyle of a graphics object with handle hobj to children, which causes each child object to have an entry in the legend:

```
hAnnotation = get(hobj,'Annotation');
hLegendEntry = get(hAnnotation,'LegendInformation');
set(hLegendEntry,'IconDisplayStyle','children')
```

Using the IconDisplayStyle Property

See "Controlling Legends" for more information and examples.

BeingDeleted

on | {off} Read Only

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions might not need to perform actions on objects if the objects are going to be deleted, and therefore, can check the object's BeingDeleted property before acting.

BusyAction

cancel | {queue}

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callbacks. If there is a callback function executing, callbacks invoked subsequently always attempt to interrupt it.

If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are

- cancel Discard the event that attempted to execute a second callback routine.
- queue Queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn

string or function handle

Button press callback function. A callback that executes whenever you press a mouse button while the pointer is over this object, but not over another graphics object. See the HitTestArea property for information about selecting objects of this type.

See the figure's SelectionType property to determine if modifier keys were also pressed.

This property can be

• A string that is a valid MATLAB expression

- The name of a MATLAB file
- A function handle

Set this property to a function handle that references the callback. The expressions execute in the MATLAB workspace.

See "Function Handle Callbacks" for information on how to use function handles to define the callbacks.

CData

vector, m-by-3 matrix, ColorSpec

Color of markers. When CData is a vector the same length as XData and YData, the values in CData are linearly mapped to the colors in the current colormap. When CData is a length(XData)-by-3 matrix, it specifies the colors of the markers as RGB values.

CDataSource

string (MATLAB variable)

Link CData to MATLAB variable. Set this property to a MATLAB variable that, by default, is evaluated in the base workspace to generate the CData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change CData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

Children

array of graphics object handles

Children of the scattergroup object. An array containing the handle of a patch object parented to the scattergroup object (whether visible or not).

If a child object's HandleVisibility property is callback or off, its handle does not show up in this object's Children property. If you want the handle in the Children property, set the root ShowHiddenHandles property to on. For example:

set(0, 'ShowHiddenHandles', 'on')

Clipping

{on} | off

Clipping mode. MATLAB clips graphs to the axes plot box by default. If you set Clipping to off, portions of graphs can be displayed outside the axes plot box. This can occur if you create a plot object, set hold to on, freeze axis scaling (axis manual), and then create a larger plot object.

CreateFcn

string or function handle

Callback routine executed during object creation. This property defines a callback that executes when MATLAB creates an object. You must specify the callback during the creation of the object. For example,

graphicfcn(y, 'CreateFcn',@CallbackFcn)

where @CallbackFcn is a function handle that references the callback function and graphicfcn is the plotting function which creates this object.

MATLAB executes this routine after setting all other object properties. Setting this property on an existing object has no effect.

The handle of the object whose CreateFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DeleteFcn

string or function handle

Callback executed during object deletion. A callback that executes when this object is deleted (e.g., this might happen when you issue a delete command on the object, its parent axes, or the figure containing it). MATLAB executes the callback before destroying the object's properties so the callback routine can query these values.

The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which can be queried using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

See the BeingDeleted property for related information.

DisplayName

string (default is empty string)

String used by legend for this scattergroup object. The legend function uses the string defined by the DisplayName property to label this scattergroup object in the legend.

- If you specify string arguments with the legend function, DisplayName is set to this scattergroup object's corresponding string and that string is used for the legend.
- If DisplayName is empty, legend creates a string of the form, ['data' n], where n is the number assigned to the object based on its location in the list of legend entries. However, legend does not set DisplayName to this string.
- If you edit the string directly in an existing legend, DisplayName is set to the edited string.
- If you specify a string for the DisplayName property and create the legend using the figure toolbar, then MATLAB uses the string defined by DisplayName.
- To add programmatically a legend that uses the DisplayName string, call legend with the toggle or show option.

See "Controlling Legends" for more examples.

EraseMode

{normal} | none | xor | background

Erase mode. This property controls the technique MATLAB uses to draw and erase objects and their children. Alternative erase modes are useful for creating animated sequences, where control of the way individual objects are redrawn is necessary to improve performance and obtain the desired effect.

• normal — Redraw the affected region of the display, performing the three-dimensional analysis necessary to ensure that all objects are rendered correctly. This mode produces the most accurate picture, but is the slowest. The other modes are faster, but do not perform a complete redraw and are therefore less accurate.

- none Do not erase objects when they are moved or destroyed. While the objects are still visible on the screen after erasing with EraseMode none, you cannot print these objects because MATLAB stores no information about their former locations.
- xor Draw and erase the object by performing an exclusive OR (XOR) with each pixel index of the screen behind it. Erasing the object does not damage the color of the objects behind it. However, the color of the erased object depends on the color of the screen behind it and it is correctly colored only when it is over the axes background color (or the figure background color if the axes Color property is set to none). That is, it isn't erased correctly if there are objects behind it.
- background Erase the graphics objects by redrawing them in the axes background color, (or the figure background color if the axes Color property is set to none). This damages other graphics objects that are behind the erased object, but the erased object is always properly colored.

Printing with Nonnormal Erase Modes

MATLAB always prints figures as if the EraseMode of all objects is normal. This means graphics objects created with EraseMode set to none, xor, or background can look different on screen than on paper. On screen, MATLAB can mathematically combine layers of colors (e.g., performing an XOR on a pixel color with that of the pixel behind it) and ignore three-dimensional sorting to obtain greater rendering speed. However, these techniques are not applied to the printed output.

Set the axes background color with the axes Color property. Set the figure background color with the figure Color property.

You can use the MATLAB getframe command or other screen capture applications to create an image of a figure containing nonnormal mode objects.

```
HandleVisibility
{on} | callback | off
```

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally accessing objects that you need to protect for some reason.

- on Handles are always visible when HandleVisibility is on.
- callback Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have access to object handles.
- off Setting HandleVisibility to off makes handles invisible at all times. This might be necessary when a callback invokes a function that might potentially damage the GUI (such as evaluating a user-typed string) and so temporarily hides its own handles during the execution of that function.

Functions Affected by Handle Visibility

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close.

Properties Affected by Handle Visibility

When a handle's visibility is restricted using callback or off, the object's handle does not appear in its parent's Children property, figures do not appear in the root's CurrentFigure property, objects do not appear in the root's CallbackObject property or in

the figure's CurrentObject property, and axes do not appear in their parent's CurrentAxes property.

Overriding Handle Visibility

You can set the root ShowHiddenHandles property to on to make all handles visible regardless of their HandleVisibility settings (this does not affect the values of the HandleVisibility properties). See also findall.

Handle Validity

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties and pass it to any function that operates on handles.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

HitTest

{on} | off

Selectable by mouse click. HitTest determines whether this object can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click on the objects that compose the area graph. If HitTest is off, clicking this object selects the object below it (which is usually the axes containing it).

```
HitTestArea
```

on | {off}

Select the object by clicking lines or area of extent. This property enables you to select plot objects in two ways:

- Select by clicking lines or markers (default).
- Select by clicking anywhere in the extent of the plot.

When HitTestArea is off, you must click the object's lines or markers (excluding the baseline, if any) to select the object. When HitTestArea is on, you can select this object by clicking anywhere within the extent of the plot (i.e., anywhere within a rectangle that encloses it).

Interruptible

{on} | off

Callback routine interruption mode. The Interruptible property controls whether an object's callback can be interrupted by callbacks invoked subsequently.

Only callbacks defined for the ButtonDownFcn property are affected by the Interruptible property. MATLAB checks for events that can interrupt a callback only when it encounters a drawnow, figure, getframe, or pause command in the routine. See the BusyAction property for related information.

Setting Interruptible to on allows any graphics object's callback to interrupt callback routines originating from a bar property. Note that MATLAB does not save the state of variables or the display (e.g., the handle returned by the gca or gcf command) when an interruption occurs.

LineWidth

scalar

The width of linear objects and edges of filled areas. Specify this value in points (1 point = $1/_{72}$ inch). The default LineWidth is 0.5 points.

Marker

character (see table)

Marker symbol. The Marker property specifies the type of markers that are displayed at plot vertices. You can set values for the Marker property independently from the LineStyle property. Supported markers include those shown in the following table.

Marker Specifier	Description
+	Plus sign
0	Circle
*	Asterisk
	Point
х	Cross
S	Square
d	Diamond
^	Upward-pointing triangle
v	Downward-pointing triangle
>	Right-pointing triangle
<	Left-pointing triangle
р	Five-pointed star (pentagram)
h	Six-pointed star (hexagram)
none	No marker (default)

MarkerEdgeColor

ColorSpec | none | {auto}

Marker edge color. The color of the marker or the edge color for filled markers (circle, square, diamond, pentagram, hexagram, and the four triangles). ColorSpec defines the color to use. none

specifies no color, which makes nonfilled markers invisible. auto sets MarkerEdgeColor to the same color as the CData property.

MarkerFaceColor

ColorSpec | {none} | auto

Marker face color. The fill color for markers that are closed shapes (circle, square, diamond, pentagram, hexagram, and the four triangles). ColorSpec defines the color to use. none makes the interior of the marker transparent, allowing the background to show through. auto sets the fill color to the axes color, or to the figure color if the axes Color property is set to none (which is the factory default for axes objects).

Parent

handle of parent axes, hggroup, or hgtransform

Parent of this object. This property contains the handle of the object's parent. The parent is normally the axes, hggroup, or hgtransform object that contains the object.

See "Objects That Can Contain Other Objects" for more information on parenting graphics objects.

Selected

on | {off}

Is object selected? When you set this property to on, MATLAB displays selection "handles" at the corners and midpoints if the SelectionHighlight property is also on (the default). You can, for example, define the ButtonDownFcn callback to set this property to on, thereby indicating that this particular object is selected. This property is also set to on when an object is manually selected in plot edit mode.

SelectionHighlight {on} | off

Objects are highlighted when selected. When the Selected property is on, MATLAB indicates the selected state by drawing four edge handles and four corner handles. When SelectionHighlight is off, MATLAB does not draw the handles except when in plot edit mode and objects are selected manually.

SizeData

square points

Size of markers in square points. This property specifies the area of the marker in the scatter graph in units of points. Since there are 72 points to one inch, to specify a marker that has an area of one square inch you would use a value of 72^2 .

SizeDataSource

string (MATLAB variable)

Link SizeData to MATLAB variable. Set this property to a MATLAB variable that, by default, is evaluated in the base workspace to generate the SizeData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change SizeData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

Тад

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when you are constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callbacks. You can define Tag as any string.

For example, you might create an areaseries object and set the Tag property.

```
t = area(Y, 'Tag', 'area1')
```

When you want to access objects of a given type, you can use findobj to find the object's handle. The following statement changes the FaceColor property of the object whose Tag is area1.

set(findobj('Tag','area1'),'FaceColor','red')

Туре

string (read only)

Type of graphics object. This property contains a string that identifies the class of the graphics object. For stemseries objects, Type is 'hggroup'. The following statement finds all the hggroup objects in the current axes.

t = findobj(gca,'Type','hggroup');

UIContextMenu

handle of a uicontextmenu object

Associate a context menu with this object. Assign this property the handle of a uicontextmenu object created in the object's parent figure. Use the uicontextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click over the object.

UserData

array

User-specified data. This property can be any data you want to associate with this object (including cell arrays and structures). The object does not set values for this property, but you can access it using the set and get functions.

Visible

{on} | off

Visibility of this object and its children. By default, a new object's visibility is on. This means all children of the object are visible unless the child object's Visible property is set to off. Setting an object's Visible property to off prevents the object from being displayed. However, the object still exists and you can set and query its properties.

XData

array

X-coordinates of scatter markers. The scatter function draws individual markers at each *x*-axis location in the XData array. The input argument x in the scatter function calling syntax assigns values to XData.

XDataSource

string (MATLAB variable)

Link XData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the XData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change XData. You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

YData

scalar, vector, or matrix

Y-coordinates of scatter markers. The scatter function draws individual markers at each *y*-axis location in the YData array.

The input argument y in the scatter function calling syntax assigns values to YData.

YDataSource

string (MATLAB variable)

Link YData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the YData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change YData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the

data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

ZData

vector of coordinates

Z-coordinates. A vector defining the *z*-coordinates for the graph. XData and YData must be the same length and have the same number of rows.

ZDataSource

string (MATLAB variable)

Link ZData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the ZData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change ZData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

schur

Purpose	Schur decomposition	
Syntax	T = schur(A) T = schur(A,flag) [U,T] = schur(A,)
Description	The schur command computes the Schur form of a matrix.	
	T = schur(A) return	as the Schur matrix T.
		for real matrix A, returns a Schur matrix T in one ng on the value of flag:
	'complex'	T is triangular and is complex if A has complex eigenvalues.
	'real'	T has the real eigenvalues on the diagonal and the complex eigenvalues in 2-by-2 blocks on the diagonal. 'real' is the default.
	If A is complex, schur returns the complex Schur form in matrix T. The complex Schur form is upper triangular with the eigenvalues of A on the diagonal.	
	The function rsf2cs Schur form.	f converts the real Schur form to the complex
<pre>[U,T] = schur(A,) also returns a unitary matrix U so f U*T*U' and U'*U = eye(size(A)).</pre>		
Examples	H is a 3-by-3 eigenvalue test matrix:	
		50 -154 80 546 -9 -25]
	Its Schur form is	
	schur(H)	

ans = 1.0000 -7.1119 -815.8706 0 2.0000 -55.0236 0 0 3.0000

The eigenvalues, which in this case are 1, 2, and 3, are on the diagonal. The fact that the off-diagonal elements are so large indicates that this matrix has poorly conditioned eigenvalues; small changes in the matrix elements produce relatively large changes in its eigenvalues.

Algorithm Input of Type Double

If A has type double, schur uses the LAPACK routines listed in the following table to compute the Schur form of a matrix:

Matrix A	Routine
Real symmetric	DSYTRD, DSTEQR
	DSYTRD, DORGTR, DSTEQR (with output U)
Real nonsymmetric	DGEHRD, DHSEQR
	DGEHRD, DORGHR, DHSEQR (with output U)
Complex Hermitian	ZHETRD, ZSTEQR
	ZHETRD, ZUNGTR, ZSTEQR (with output U)
Non-Hermitian	ZGEHRD, ZHSEQR
	ZGEHRD, ZUNGHR, ZHSEQR (with output U)

Input of Type Single

If A has type single, schur uses the LAPACK routines listed in the following table to compute the Schur form of a matrix:

Matrix A	Routine
Real symmetric	SSYTRD, SSTEQR
	SSYTRD, SORGTR, SSTEQR (with output U)
Real nonsymmetric	SGEHRD, SHSEQR
	SGEHRD, SORGHR, SHSEQR (with $output U$)
Complex Hermitian	CHETRD, CSTEQR
	CHETRD, CUNGTR, CSTEQR (with output U)
Non-Hermitian	CGEHRD, CHSEQR
	CGEHRD, CUNGHR, CHSEQR (with output U)

See Also eig, hess, qz, rsf2csf

References [1] Anderson, E., Z. Bai, C. Bischof, S. Blackford, J. Demmel, J. Dongarra, J. Du Croz, A. Greenbaum, S. Hammarling, A. McKenney, and D. Sorensen, *LAPACK User's Guide* (http://www.netlib.org/lapack/lug/lapack_lug.html), Third Edition, SIAM, Philadelphia, 1999.

Purpose Sequence of MATLAB statements in file **Description** A script file is an external file that contains a sequence of MATLAB statements. By typing the filename, you can obtain subsequent MATLAB input from the file. Script files have a filename extension of .m. Scripts are the simplest kind of MATLAB program. They are useful for automating blocks of MATLAB commands, such as computations you have to perform repeatedly from the command line. Scripts can operate on existing data in the workspace, or they can create new data on which to operate. Although scripts do not return output arguments, any variables that they create remain in the workspace, so you can use them in further computations. In addition, scripts can produce graphical output using commands like plot. Scripts can contain any series of MATLAB statements. They require no declarations or begin/end delimiters. Like any MATLAB program, scripts can contain comments. Any text following a percent sign (%) on a given line is comment text. Comments can appear on lines by themselves, or you can append them to the end of any executable line. See Also echo, function, type

Purpose	Secant of argument in radians	
Syntax	Y = sec(X)	
Description	The sec function operates element-wise on arrays. The function's domains and ranges include complex values. All angles are in radians.	
	Y = sec(X) returns an array the same size as X containing the secant of the elements of X.	
Examples	Graph the secant over the domains $-\pi/2 < x < \pi/2$ and $\pi/2 < x < 3\pi/2$.	
	<pre>x1 = -pi/2+0.01:0.01:pi/2-0.01; x2 = pi/2+0.01:0.01:(3*pi/2)-0.01; plot(x1,sec(x1),x2,sec(x2)), grid on</pre>	
	150	
	100	
	50	
	-50	
	-100	
	-150 -2 -1 0 1 2 3 4 5	

The expression sec(pi/2) does not evaluate as infinite but as the reciprocal of the floating-point accuracy eps, because pi is a floating-point approximation to the exact value of π .

Definition The secant can be defined as

$$\sec(z) = \frac{1}{\cos(z)}$$

- Algorithm sec uses FDLIBM, which was developed at SunSoft, a Sun Microsystems, Inc. business, by Kwok C. Ng, and others. For information about FDLIBM, see http://www.netlib.org.
- See Also secd, sech, asec, asecd, asech

Purpose	Secant of argument in degrees
Syntax	Y = secd(X)
Description	Y = secd(X) is the secant of the elements of X, expressed in degrees. For odd integers n, secd(n*90) is infinite, whereas sec(n*pi/2) is large but finite, reflecting the accuracy of the floating point value of pi.
See Also	sec, sech, asec, asecd, asech

Purpose	Hyperbolic secant
Syntax	Y = sech(X)
Description	The sech function operates element-wise on arrays. The function's domains and ranges include complex values. All angles are in radians.
	Y = sech(X) returns an array the same size as X containing the hyperbolic secant of the elements of X.
Examples	Graph the hyperbolic secant over the domain $-2\pi \le x \le 2\pi$.
	<pre>x = -2*pi:0.01:2*pi; plot(x,sech(x)), grid on</pre>
	0.9
	0.8
	0.7
	0.6
	0.5
	0.4
	0.3
	0.2
	0.1
	-8 -6 -4 -2 0 2 4 6 8

Algorithm	sech uses this algorithm.
	$\operatorname{sech}(z) = \frac{1}{\cosh(z)}$
Definition	The secant can be defined as
	$\operatorname{sech}(z) = \frac{1}{\cosh(z)}$
Algorithm	<pre>sec uses FDLIBM, which was developed at SunSoft, a Sun Microsystems, Inc. business, by Kwok C. Ng, and others. For information about FDLIBM, see http://www.netlib.org.</pre>
See Also	asec, asech, sec

Purpose	Select, move, resize, or copy axes and uicontrol graphics objects
Syntax	A = selectmoveresize set(gca,'ButtonDownFcn','selectmoveresize')
Description	selectmoveresize is useful as the callback routine for axes and uicontrol button down functions. When executed, it selects the object and allows you to move, resize, and copy it.
	A = selectmoveresize returns a structure array containing
	• A.Type: a string containing the action type, which can be Select, Move, Resize, or Copy
	• A.Handles: a list of the selected handles, or, for a Copy, an m-by-2 matrix containing the original handles in the first column and the new handles in the second column
	<pre>set(gca, 'ButtonDownFcn', 'selectmoveresize') sets the ButtonDownFcn property of the current axes to selectmoveresize:</pre>
See Also	The ButtonDownFcn property of axes and uicontrol objects
	"Object Manipulation" on page 1-110 for related functions

semilogx, semilogy

Purpose

Semilogarithmic plots




\mathcal{A}	1	١		
			V	

✓ plot(t,y) GUI To graph selected variables, use the Plot Selector in the **Alternatives** Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in *plot edit* mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation. Syntax semilogx(Y) semilogy(...) semilogx(X1,Y1,...) semilogx(X1,Y1,LineSpec,...) semilogx(...,'PropertyName', PropertyValue,...) h = semilogx(...)h = semilogy(...)Description semilogx and semilogy plot data as logarithmic scales for the x- and y-axis, respectively. semilogx(Y) creates a plot using a base 10 logarithmic scale for the *x*-axis and a linear scale for the *y*-axis. It plots the columns of Y versus their index if Y contains real numbers. semilogx(Y) is equivalent to semilogx(real(Y), imag(Y)) if Y contains complex numbers. semilogx ignores the imaginary component in all other uses of this function. semilogy(...) creates a plot using a base 10 logarithmic scale for the *y*-axis and a linear scale for the *x*-axis. semilogx(X1,Y1,...) plots all Xn versus Yn pairs. If only Xn or Yn is a matrix, semilogx plots the vector argument versus the rows or columns of the matrix, depending on whether the vector's row or column dimension matches the matrix.

semilogx(X1,Y1,LineSpec,...) plots all lines defined by the Xn, Yn, LineSpec triples. LineSpec determines line style, marker symbol, and color of the plotted lines. semilogx(..., 'PropertyName', PropertyValue,...) sets property values for all lineseries graphics objects created by semilogx. h = semilogx(...) and h = semilogy(...) return a vector of handles to lineseries graphics objects, one handle per line. Remarks If you do not specify a color when plotting more than one line, semilogx and semilogy automatically cycle through the colors and line styles in the order specified by the current axes ColorOrder and LineStyleOrder properties. You can mix Xn, Yn pairs with Xn, Yn, LineSpec triples; for example, semilogx(X1,Y1,X2,Y2,LineSpec,X3,Y3) If you attempt to add a loglog, semilogx, or semilogy plot to a linear axis mode graph with hold on, the axis mode will remain as it is and the new data will plot as linear. **Examples** Create a simple semilogy plot. x = 0:.1:10; $semilogy(x, 10.^x)$

semilogx, semilogy





line, LineSpec, loglog, plot "Basic Plots and Graphs" on page 1-96 for related functions

Purpose	Send e-mail message to address list
Syntax	<pre>sendmail('recipients','subject') sendmail('recipients','subject','message') sendmail('recipients','subject','message','attachments')</pre>
Description	<pre>sendmail('recipients','subject') sends e-mail to recipients with the specified subject. The recipients input is a string for a single address, or a cell array of strings for multiple addresses.</pre>
	<pre>sendmail('recipients', 'subject', 'message') includes the specified message. If message is a string, sendmail automatically wraps text at 75 characters. To force a line break in the message text, use 10, as shown in the Examples. If message is a cell array of strings, each cell represents a new line of text.</pre>
	<pre>sendmail('recipients','subject','message','attachments') attaches the files listed in the string or cell array attachments.</pre>
Tips	• The sendmail function does not support e-mail servers that require authentication.
	• If sendmail cannot determine your e-mail address or outgoing SMTP mail server from your system registry, specify those settings using the setpref function. For example:
	setpref('Internet','SMTP_Server','myserver.myhost.com'); setpref('Internet','E_mail','myaddress@example.com');
	To identify the SMTP server for the call to setpref, check the preferences for your electronic mail application, or consult your e-mail system administrator. If you cannot easily determine the server name, try 'mail', which is a common default, such as:
	<pre>setpref('Internet','SMTP_Server','mail');</pre>
	• The sendmail function does not support HTML-formatted messages. However, you can send HTML files as attachments.

sendmail

Examples	Send a message with two attachments to a hypothetical e-mail address: sendmail('user@otherdomain.com',
	'Test subject','Test message', {'directory/attach1.html','attach2.doc'});
	Send a message with forced line breaks (using 10) to a hypothetical e-mail address:
	sendmail('user@otherdomain.com','New subject', ['Line1 of message' 10 'Line2 of message' 10 'Line3 of message' 10 'Line4 of message']);
	The resulting message is:
	Line1 of message
	Line2 of message Line3 of message
	Line4 of message
Alternatives	On Windows systems with Microsoft [®] Outlook [®] , you can send e-mail directly through Outlook [®] by accessing the COM server with actxserver. For an example, see Solution 1-RTY6J.
See Also	getpref setpref
How To	"Specifying Proxy Server Settings"

Purpose	Create serial port object
Syntax	obj = serial('port') obj = serial('port','PropertyName',PropertyValue,)
Description	

Description obj = serial('port') creates a serial port object associated with the serial port specified by port. If port does not exist, or if it is in use, you will not be able to connect the serial port object to the device.

Port object name will depend upon the platform that the serial port is on. instrhwinfo ('serial') provides a list of available serial ports. This list is an example of serial constructors on different platforms:

Platform	Serial Port Constructor
Linux and Linux 64	<pre>serial('/dev/ttyS0');</pre>
Mac OS X and Mac OS X 64	<pre>serial('/dev/tty.KeySerial1');</pre>
Solaris 64	<pre>serial('/dev/term/a');</pre>
Windows 32 and Windows 64	<pre>serial('com1');</pre>

obj = serial('port', 'PropertyName', PropertyValue,...) creates a serial port object with the specified property names and property values. If an invalid property name or property value is specified, an error is returned and the serial port object is not created.

Remarks When you create a serial port object, these property values are automatically configured:

- The Type property is given by serial.
- The Name property is given by concatenating Serial with the port specified in the serial function.
- The Port property is given by the port specified in the serial function.

You can specify the property names and property values using any format supported by the set function. For example, you can use property name/property value cell array pairs. Additionally, you can specify property names without regard to case, and you can make use of property name completion. For example, the following commands are all valid on a Windows platform.

```
s = serial('COM1','BaudRate',4800);
s = serial('COM1','baudrate',4800);
s = serial('COM1','BAUD',4800);
```

Refer to Configuring Property Values for a list of serial port object properties that you can use with serial.

Before you can communicate with the device, it must be connected to obj with the fopen function. A connected serial port object has a Status property value of open. An error is returned if you attempt a read or write operation while the object is not connected to the device. You can connect only one serial port object to a given serial port.

Example This example creates the serial port object s1 associated with the serial port COM1 on a Windows platform.

s1 = serial('COM1');

The Type, Name, and Port properties are automatically configured.

```
get(s1,{'Type','Name','Port'})
ans =
    'serial' 'Serial-COM1' 'COM1'
```

To specify properties during object creation

```
s2 = serial('COM2', 'BaudRate', 1200, 'DataBits', 7);
```

See Also Functions

fclose, fopen

Properties

Name, Port, Status, Type

serialbreak

Purpose	Send break to device connected to serial port
Syntax	serialbreak(obj) serialbreak(obj,time)
Description	serialbreak(obj) sends a break of 10 milliseconds to the device connected to the serial port object, obj.
	<pre>serialbreak(obj,time) sends a break to the device with a duration, in milliseconds, specified by time. Note that the duration of the break might be inaccurate under some operating systems.</pre>
Remarks	For some devices, the break signal provides a way to clear the hardware buffer.
	Before you can send a break to the device, it must be connected to obj with the fopen function. A connected serial port object has a Status property value of open. An error is returned if you attempt to send a break while obj is not connected to the device.
	serialbreak is a synchronous function, and blocks the command line until execution is complete.
	If you issue serialbreak while data is being asynchronously written, an error is returned. In this case, you must call the stopasync function or wait for the write operation to complete.
See Also	Functions
	fopen, stopasync
	Properties

Status

Purpose	Set Handle Graphics object properties
Syntax	<pre>set(H, 'PropertyName', PropertyValue,) set(H,a) set(H,pn,pv,) set(H,pn,MxN_pv) a = set(h) pv = set(h, 'PropertyName')</pre>

Description

Note Do not use the set function on Java objects as it will cause a memory leak. For more information, see "Accessing Private and Public Data"

set(H, 'PropertyName', PropertyValue,...) sets the named properties to the specified values on the object(s) identified by H. H can be a vector of handles, in which case set sets the properties' values for all the objects.

set(H,a) sets the named properties to the specified values on the object(s) identified by H. a is a structure array whose field names are the object property names and whose field values are the values of the corresponding properties.

set(H,pn,pv,...) sets the named properties specified in the cell array pn to the corresponding value in the cell array pv for all objects identified in H.

set(H,pn,MxN_pv) sets n property values on each of m graphics objects, where m = length(H) and n is equal to the number of property names contained in the cell array pn. This allows you to set a given group of properties to different values on each object.

a = set(h) returns the user-settable properties and possible values for the object identified by h. a is a structure array whose field names are the object's property names and whose field values are the possible values of the corresponding properties. If you do not specify an output argument, the MATLAB software displays the information on the screen. h must be scalar.

pv = set(h, 'PropertyName') returns the possible values for the named property. If the possible values are strings, set returns each in a cell of the cell array pv. For other properties, set returns a statement indicating that PropertyName does not have a fixed set of property values. If you do not specify an output argument, MATLAB displays the information on the screen. h must be scalar.

Remarks You can use any combination of property name/property value pairs, structure arrays, and cell arrays in one call to set.

Setting Property Units

Note that if you are setting both the FontSize and the FontUnits properties in one function call, you must set the FontUnits property first so that the MATLAB software can correctly interpret the specified FontSize. The same applies to figure and axes uints — always set the Units property before setting properties whose values you want to be interpreted in those units. For example,

f = figure('Units','characters',... 'Position',[30 30 120 35]);

Examples Set the Color property of the current axes to blue.

```
axes;
set(gca,'Color','b')
```

Change all the lines in a plot to black.

```
plot(peaks)
set(findobj('Type','line'),'Color','k')
```

You can define a group of properties in a structure to better organize your code. For example, these statements define a structure called active, which contains a set of property definitions used for the uicontrol objects in a particular figure. When this figure becomes the current figure, MATLAB changes the colors and enables the controls.

```
active.BackgroundColor = [.7 .7 .7];
active.Enable = 'on';
active.ForegroundColor = [0 0 0];
if gcf == control_fig_handle
set(findobj(control_fig_handle,'Type','uicontrol'),active)
end
```

You can use cell arrays to set properties to different values on each object. For example, these statements define a cell array to set three properties,

```
PropName(1) = {'BackgroundColor'};
PropName(2) = {'Enable'};
PropName(3) = {'ForegroundColor'};
```

These statements define a cell array containing three values for each of three objects (i.e., a 3-by-3 cell array).

```
PropVal(1,1) = {[.5 .5 .5]};
PropVal(1,2) = {'off'};
PropVal(1,3) = {[.9 .9 .9]};
PropVal(2,1) = {[1 0 0]};
PropVal(2,2) = {'on'};
PropVal(2,3) = {[1 1 1]};
PropVal(3,1) = {[.7 .7 .7]};
PropVal(3,2) = {'on'};
PropVal(3,3) = {[0 0 0]};
```

Now pass the arguments to set,

```
set(H,PropName,PropVal)
```

where length(H) = 3 and each element is the handle to a uicontrol.

Setting Different Values for the Same Property on Multiple Objects

Suppose you want to set the value of the Tag property on five line objects, each to a different value. Note how the value cell array needs to be transposed to have the proper shape.

```
h = plot(rand(5));
set(h,{'Tag'},{'line1','line2','line3','line4','line5'}')
```

See Also findobj, gca, gcf, gco, gcbo, get

"Graphics Object Identification" on page 1-103 for related functions

Purpose	Set property values for audioplayer object
Syntax	<pre>set(obj, 'PropertyName', Value) set(obj, cellOfNames, cellOfValues) set(obj, structOfProperties) settableProperties = set(obj)</pre>
Description	<pre>set(obj, 'PropertyName', Value) sets the named property to the specified value for the object obj.</pre>
	<pre>set(obj, cellOfNames, cellOfValues) sets the properties listed in the cell array cellOfNames to the corresponding values in the cell array cellOfValues. Each cell array must contain the same number of elements.</pre>
	<pre>set(obj, structOfProperties) sets the properties identified by each field of the structure array structOfProperties to the values of the associated fields.</pre>
	<pre>settableProperties = set(obj) returns the names of the properties that you can set in a structure array. The field names of settableProperties are the property names.</pre>
Tips	The set function allows combinations of property name/value pairs, cell array pairs, and structure arrays in the same function call.
Examples	View the list of properties that you can set for an audioplayer object:
	load handel.mat; handelObj = audioplayer(y, Fs); set(handelObj)

Set the Tag and UserData properties of an ${\tt audioplayer}$ object using a structure array:

```
newValues.Tag = 'My Tag';
newValues.UserData = {'My User Data', pi, [1 2 3 4]};
```

	load handel.mat; handelObj = audioplayer(y, Fs); set(handelObj, newValues) % View the values all properties. get(handelObj)
Alternatives	To set the value of a single property, you can use dot notation. Reference each property as though it is a field of a structure array. For example, set the Tag property for an object called handelObj (as created in the Examples):
	handelObj.Tag = 'This is my tag.';
	This command is exactly equivalent to:
	<pre>set(handelObj, 'Tag', 'This is my tag.');</pre>
See Also	audioplayer get

Purpose	Set property values for audiorecorder object
Syntax	<pre>set(obj, 'PropertyName', Value) set(obj, cellOfNames, cellOfValues) set(obj, structOfProperties) settableProperties = set(obj)</pre>
Description	<pre>set(obj, 'PropertyName', Value) sets the named property to the specified value for the object obj.</pre>
	<pre>set(obj, cellOfNames, cellOfValues) sets the properties listed in the cell array cellOfNames to the corresponding values in the cell array cellOfValues. Each cell array must contain the same number of elements.</pre>
	<pre>set(obj, structOfProperties) sets the properties identified by each field of the structure array structOfProperties to the values of the associated fields.</pre>
	<pre>settableProperties = set(obj) returns the names of the properties that you can set in a structure array. The field names of settableProperties are the property names.</pre>
Tips	The set function allows combinations of property name/value pairs, cell array pairs, and structure arrays in the same function call.
Examples	<pre>View the list of properties that you can set for an audiorecorder object: recorderObj = audiorecorder; set(recorderObj)</pre>
	Set the Tag and UserData properties of an audiorecorder object using a structure array:

```
newValues.Tag = 'My Tag';
newValues.UserData = {'My User Data', pi, [1 2 3 4]};
```

	recorderObj = audiorecorder; set(recorderObj, newValues)
	% View the values all properties. get(recorderObj)
Alternatives	To set the value of a single property, you can use dot notation. Reference each property as though it is a field of a structure array. For example, set the Tag property for an object called recorderObj (as created in the Examples):
	<pre>recorderObj.Tag = 'This is my tag.';</pre>
	This command is exactly equivalent to:
	<pre>set(recorderObj, 'Tag', 'This is my tag.');</pre>
See Also	audiorecorder get

Purpose	Set object or interface property to specified value
Syntax	h.set('pname', value) h.set('pname1', value1, 'pname2', value2,) set(h,)
Description	h.set('pname', value) sets the property specified in the string pname to the given value.
	h.set('pname1', value1, 'pname2', value2,) sets each property specified in the pname strings to the given value.
	$set(h, \ldots)$ is an alternate syntax for the same operation.
	See "Handling COM Data in MATLAB Software" in the External Interfaces documentation for information on how MATLAB converts workspace matrices to COM data types.
Remarks	COM functions are available on Microsoft Windows systems only.
Examples	Create an mwsamp control and use set to change the Label and Radius properties:
	f = figure ('position', [100 200 200 200]); h = actxcontrol ('mwsamp.mwsampctrl.1', [0 0 200 200], f);
	h.set('Label', 'Click to fire event', 'Radius', 40); h.invoke('Redraw');
	Here is another way to do the same thing, only without set and invoke:
	h.Label = 'Click to fire event'; h.Radius = 40; h.Redraw;
See Also	get (COM), inspect, isprop, addproperty, deleteproperty

Purpose	Assign property values to handle objects derived from hgsetget class
Syntax	<pre>set(H,'PropertyName',value,) set(H,pn,pv) set(H,S) pv = set(h,'PropertyName') S = set(h)</pre>
Description	<pre>set(H, 'PropertyName', value,) sets the named property to the specified value for the objects in the handle array H.</pre>
	<pre>set(H,pn,pv) sets the named properties specified in the cell array of strings pn to the corresponding values in the cell array pv for all objects specified in H. The cell array pn must be 1-by-n, but the cell array pv can be m-by-n where m is equal to length(H). set updates each object with a different set of values for the list of property names contained in pn.</pre>
	<pre>set(H,S) sets the properties identified by each field name of struct S with the values contained in S. S is a struct whose field names are object property names.</pre>
	<pre>pv = set(h, 'PropertyName') returns the possible values for the named property.</pre>
	S = set(h) returns the user-settable properties and possible values for the handle object h. S is a struct whose field names are the object's property names and whose values are cell arrays containing the possible values of the corresponding properties. The cell array is empty for properties that do not have finite possible values.
	You can use property/value string pairs, structs, and property/value cell array pairs in the same call to set.
	Override the hgsetget class setdisp method to change how MATLAB displays this information.
See Also	See "Implementing a Set/Get Interface for Properties"
	handle, hgsetget, set, get (hgsetget)

Purpose	Set property values for multimedia reader object
Syntax	<pre>set(obj, 'PropertyName', Value) set(obj, cellOfNames, cellOfValues) set(obj, structOfProperties) settableProperties = set(obj)</pre>
Description	<pre>set(obj, 'PropertyName', Value) sets the named property to the specified value for the object obj.</pre>
	<pre>set(obj, cellOfNames, cellOfValues) sets the properties listed in the cell array cellOfNames to the corresponding values in the cell array cellOfValues. Each cell array must contain the same number of elements.</pre>
	<pre>set(obj, structOfProperties) sets the properties identified by each field of the structure array structOfProperties to the values of the associated fields.</pre>
	<pre>settableProperties = set(obj) returns the names of the properties that you can set in a structure array. The field names of settableProperties are the property names.</pre>
Tips	The set function allows combinations of property name/value pairs, cell array pairs, and structure arrays in the same function call.
Examples	View the list of properties that you can set for a multimedia reader object:
	<pre>xyloObj = mmreader('xylophone.mpg'); set(xyloObj)</pre>
	Set the Tag and UserData properties of a multimedia reader object

using a structure array:

```
newValues.Tag = 'My Tag';
newValues.UserData = {'My User Data', pi, [1 2 3 4]};
```

	xyloObj = mmreader('xylophone.mpg'); set(xyloObj, newValues) % View the values all properties. get(xyloObj)
Alternatives	To set the value of a single property, you can use dot notation. Reference each property as though it is a field of a structure array. For example, set the Tag property for a reader object called xyloObj (as created in the Examples):
	<pre>xyloObj.Tag = 'This is my tag.';</pre>
	This command is exactly equivalent to:
	<pre>set(xyloObj, 'Tag', 'This is my tag.');</pre>
See Also	mmreader get

Purpose	Set random stream property
Class	@RandStream
Syntax	<pre>set(S,'PropertyName',Value) set(S,'Property1',Value1,'Property2',Value2,) set(S,A) A=set(S,'Property') set(S,'Property') A=set(S) set(S)</pre>
Description	<pre>set(S, 'PropertyName',Value) sets the property 'PropertyName' of the random stream S to the value Value.</pre>
	<pre>set(S, 'Property1', Value1, 'Property2', Value2,) sets multiple random stream property values with a single statement.</pre>
	set(S,A) where A is a structure whose field names are property names of the random stream S sets the properties of S named by each field with the values contained in those fields.
	A=set(S, 'Property') or set(S, 'Property') displays possible values for the specified property of S.
	A=set(S) or set(S) displays or returns all properties of S and their possible values.
See Also	@RandStream, get (RandStream), rand, randn, randi

<u>set (serial)</u>

Purpose	Configure or display serial port object properties
Syntax	<pre>set(obj) props = set(obj) set(obj,'PropertyName') props = set(obj,'PropertyName') set(obj,'PropertyName',PropertyValue,) set(obj,PN,PV) set(obj,S)</pre>
Description	set(obj) displays all configurable properties values for the serial port object, obj. If a property has a finite list of possible string values, then these values are also displayed.
	<pre>props = set(obj) returns all configurable properties and their possible values for obj to props. props is a structure whose field names are the property names of obj, and whose values are cell arrays of possible property values. If the property does not have a finite set of possible values, then the cell array is empty.</pre>
	<pre>set(obj, 'PropertyName') displays the valid values for PropertyName if it possesses a finite list of string values.</pre>
	<pre>props = set(obj, 'PropertyName') returns the valid values for PropertyName to props. props is a cell array of possible string values or an empty cell array if PropertyName does not have a finite list of possible values.</pre>
	set(obj,' <i>PropertyName</i> ',PropertyValue,) configures multiple property values with a single command.
	set(obj,PN,PV) configures the properties specified in the cell array of strings PN to the corresponding values in the cell array PV. PN must be a vector. PV can be m-by-n where m is equal to the number of serial port objects in obj and n is equal to the length of PN.
	<pre>set(obj,S) configures the named properties to the specified values for obj. S is a structure whose field names are serial port object properties, and whose field values are the values of the corresponding properties.</pre>

Remarks	Refer to Configuring Property Values for a list of serial port object
	properties that you can configure with set.

You can use any combination of property name/property value pairs, structures, and cell arrays in one call to set. Additionally, you can specify a property name without regard to case, and you can make use of property name completion. For example, if s is a serial port object, then the following commands are all valid.

```
set(s,'BaudRate')
set(s,'baudrate')
set(s,'BAUD')
```

If you use the help command to display help for set, then you need to supply the pathname shown below.

help serial/set

Examples This example illustrates some of the ways you can use set to configure or return property values for the serial port object s, on a Windows platform.

s = serial('COM1'); set(s, 'BaudRate',9600, 'Parity', 'even') set(s, {'StopBits', 'RecordName'}, {2, 'sydney.txt'}) set(s, 'Parity') [{none} | odd | even | mark | space]

See Also Functions

get

set (timer)

Purpose	Configure or display timer object properties
Syntax	<pre>set(obj) prop_struct = set(obj) set(obj,'PropertyName') prop_cell=set(obj,'PropertyName') set(obj,'PropertyName',PropertyValue,) set(obj,S) set(obj,PN,PV)</pre>
Description	<pre>set(obj) displays property names and their possible values for all configurable properties of timer object obj. obj must be a single timer object.</pre>
	<pre>prop_struct = set(obj) returns the property names and their possible values for all configurable properties of timer object obj. obj must be a single timer object. The return value, prop_struct, is a structure whose field names are the property names of obj, and whose values are cell arrays of possible property values or empty cell arrays if the property does not have a finite set of possible string values.</pre>
	<pre>set(obj,'PropertyName') displays the possible values for the specified property, PropertyName, of timer object obj. obj must be a single timer object.</pre>
	<pre>prop_cell=set(obj, 'PropertyName') returns the possible values for the specified property, PropertyName, of timer object obj. obj must be a single timer object. The returned array, prop_cell, is a cell array of possible value strings or an empty cell array if the property does not have a finite set of possible string values.</pre>
	<pre>set(obj,'PropertyName', PropertyValue,) configures the property, PropertyName, to the specified value, PropertyValue, for timer object obj. You can specify multiple property name/property value pairs in a single statement. obj can be a single timer object or a vector of timer objects, in which case set configures the property values for all the timer objects specified.</pre>

set(obj,S) configures the properties of obj, with the values specified
in S, where S is a structure whose field names are object property names.

set(obj,PN,PV) configures the properties specified in the cell array of strings, PN, to the corresponding values in the cell array PV, for the timer object obj. PN must be a vector. If obj is an array of timer objects, PV can be an M-by-N cell array, where M is equal to the length of timer object array and N is equal to the length of PN. In this case, each timer object is updated with a different set of values for the list of property names contained in PN.

Note When specifying parameter/value pairs, you can use any mixture of strings, structures, and cell arrays in the same call to set.

Examples Create a timer object.

```
t = timer;
```

Display all configurable properties and their possible values.

```
set(t)
BusyMode: [ {drop} | queue | error ]
ErrorFcn: string -or- function handle -or- cell array
ExecutionMode: [ {singleShot} | fixedSpacing | fixedDelay | fixedRate ]
Name
ObjectVisibility: [ {on} | off ]
Period
StartDelay
StartFcn: string -or- function handle -or- cell array
StopFcn: string -or- function handle -or- cell array
Tag
TasksToExecute
TimerFcn: string -or- function handle -or- cell array
UserData
```

View the possible values of the ExecutionMode property.

```
set(t, 'ExecutionMode')
[ {singleShot} | fixedSpacing | fixedDelay | fixedRate ]
```

Set the value of a specific timer object property.

set(t, 'ExecutionMode', 'FixedRate')

Set the values of several properties of the timer object.

set(t, 'TimerFcn', 'callbk', 'Period', 10)

Use a cell array to specify the names of the properties you want to set and another cell array to specify the values of these properties.

set(t, {'StartDelay', 'Period'}, {30, 30})

See Also timer, get(timer)

Purpose	Set properties of timeseries object
Syntax	<pre>set(ts,'Property',Value) set(ts,'Property1',Value1,'Property2',Value2,) set(ts,'Property') set(ts)</pre>
Description	<pre>set(ts, 'Property', Value) sets the property 'Property' of the timeseries object ts to the value Value. The following syntax is equivalent: ts.Property = Value</pre>
	set(ts,'Property1',Value1,'Property2',Value2,) sets multiple property values for ts with a single statement.
	<pre>set(ts,'Property') displays values for the specified property of the timeseries object ts.</pre>
	<pre>set(ts) displays all properties and values of the timeseries object ts.</pre>
See Also	get (timeseries)

set (tscollection)

Purpose	Set properties of tscollection object
Syntax	set(tsc,'Property',Value) set(tsc,'Property1',Value1,'Property2',Value2,) set(tsc,'Property')
Description	<pre>set(tsc, 'Property', Value) sets the property 'Property' of the tscollection tsc to the value Value. The following syntax is equivalent: tsc.Property = Value</pre>
	set(tsc, 'Property1', Value1, 'Property2', Value2,) sets multiple property values for tsc with a single statement.
	<pre>set(tsc, 'Property') displays values for the specified property in the time-series collection tsc.</pre>
	set(tsc) displays all properties and values of the <code>tscollection</code> object <code>tsc</code> .
See Also	get (tscollection)

Purpose	Set times of timeseries object as date strings
Syntax	ts = setabstime(ts,Times) ts = setabstime(ts,Times,Format)
Description	<pre>ts = setabstime(ts,Times) sets the times in ts to the date strings specified in Times. Times must either be a cell array of strings, or a char array containing valid date or time values in the same date format.</pre>
	<pre>ts = setabstime(ts,Times,Format) explicitly specifies the date-string format used in Times.</pre>
Examples	1 Create a time-series object.
	<pre>ts = timeseries(rand(3,1))</pre>
	2 Set the absolute time vector.
	ts = setabstime(ts,{'12-DEC-2005 12:34:56', '12-DEC-2005 13:34:56','12-DEC-2005 14:34:56'})
See Also	datestr, getabstime (timeseries), timeseries

setabstime (tscollection)

Purpose	Set times of tscollection object as date strings
Syntax	tsc = setabstime(tsc,Times) tsc = setabstime(tsc,Times,format)
Description	<pre>tsc = setabstime(tsc,Times) sets the times in tsc using the date strings Times. Times must be either a cell array of strings, or a char array containing valid date or time values in the same date format. tsc = setabstime(tsc,Times,format) specifies the date-string</pre>
	format used in Times explicitly.
Examples	1 Create a tscollection object.
	<pre>tsc = tscollection(timeseries(rand(3,1)))</pre>
	2 Set the absolute time vector.
	tsc = setabstime(tsc,{'12-DEC-2005 12:34:56', '12-DEC-2005 13:34:56','12-DEC-2005 14:34:56'})
See Also	datestr, getabstime (tscollection), tscollection

Purpose	Specify application-defined data
Syntax	<pre>setappdata(h,'name',value)</pre>
Description	<pre>setappdata(h, 'name', value) sets application-defined data for the object with handle h. The application-defined data, which is created if it does not already exist, is assigned the specified name and value. The value can be any type of data.</pre>
Remarks	Application data is data that is meaningful to or defined by your application which you attach to a figure or any GUI component (other than ActiveX controls) through its AppData property. Only Handle Graphics MATLAB objects use this property.
See Also	getappdata, isappdata, rmappdata

setDefaultStream (RandStream)

Purpose	Set default random number stream
Syntax	prevstream = RandStream.setDefaultStream(stream)
Description	prevstream = RandStream.setDefaultStream(stream) returns the current default random number stream, and designates the random number stream stream as the new default to be used by the rand, randi, and randn functions.
	rand, randi, and randn all rely on the same stream of uniform pseudorandom numbers, known as the default stream. randi uses one uniform value from the default stream to generate each integer value. randn uses one or more uniform values from the default stream to generate each normal value. Note that there are also rand, randi, and randn methods for which you specify a specific random stream from which to draw values.
See Also	getDefaultStream (RandStream),@RandStream,rand (RandStream), randn (RandStream),randperm (RandStream)

Purpose	Find set difference of two vectors									
Syntax	c = setdiff(A, B) c = setdiff(A, B, 'rows') [c,i] = setdiff()									
Description	c = setdiff(A, B) returns the values in A that are not in B. In set theory terms, $c = A - B$. Inputs A and B can be numeric or character vectors or cell arrays of strings. The resulting vector is sorted in ascending order.									
	c = setdit same numb		-							
	[c,i] = se c = a(i) o				eturns a	an inde	ex vecto	rindex	such tl	hat
Remarks	Because Na result c if i			ed to be	e not eq	ual to i	tself, it	is alwa	ays in tl	ne
Examples	A = mag B = mag [c, i] c' = i' =	ic(4); = setd 17	liff(A) 18	19	20	21 19	22 23	23 2	24 6	25 15
See Also	intersect,	ismem	ber,is	sorted	, setxo	r,unio	on, unic	que		

Tiff.setDirectory

Purpose	Make specified IFD current IFD					
Syntax	tiffobj.setDirectory(dirNum)					
Description	tiffobj.setDirectory(dirNum) sets the image file directory (IFD) specified by dirNum as the current IFD. Tiff object methods operate on the current IFD. The directory index number is one-based.					
Examples	Open a TIFF file and move to an IFD in the file by specifying its index number. Replace myfile.tif with the name of a TIFF file on your MATLAB path. The TIFF file should contain multiple images.					
	<pre>t = Tiff('myfile.tif','r'); t.setDirectory(2);</pre>					
References	This method corresponds to the TIFFSetDirectory function in the LibTIFF C API. To use this method, you must be familiar with LibTIFF version 3.7.1 as well as the TIFF specification and technical notes. View this documentation at LibTIFF - TIFF Library and Utilities.					
See Also	Tiff.currentDirectory Tiff.nextDirectory					
Tutorials	"Exporting Image Data and Metadata to TIFF Files""Reading Image Data and Metadata from TIFF Files"					

Purpose	Override to change command window display
Syntax	setdisp(H)
Description	<pre>setdisp(H) called by set when set is called with no output arguments and a single input argument that is a handle array. Override this hgsetget class method in a subclass to change how property information is displayed in the command window.</pre>
See Also	See "Implementing a Set/Get Interface for Properties" hgsetget, set (hgsetget)

setenv

Purpose	Set environment variable
Syntax	setenv(name, value) setenv(name)
Description	<pre>setenv(name, value) sets the value of an environment variable belonging to the underlying operating system. Inputs name and value are both strings. If name already exists as an environment variable, then setenv replaces its current value with the string given in value. If name does not exist, setenv creates a new environment variable called name and assigns value to it.</pre>
	setenv(name) is equivalent to setenv(name, '') and assigns a null value to the variable name. On the Microsoft Windows platform, this is equivalent to undefining the variable. On most UNIX ¹⁶ platforms, it is possible to have an environment variable defined as empty.
	The maximum number of characters in name is 2^{15} - 2 (or 32766). If name contains the character =, setenv throws an error. The behavior of environment variables with = in the name is not well-defined.
	On all platforms, setenv passes the name and value strings to the operating system unchanged. Special characters such as ;, /, :, \$, %, etc. are left unexpanded and intact in the variable value.
	Values assigned to variables using setenv are picked up by any process that is spawned using the MATLAB system, unix, dos or ! functions. You can retrieve any value set with setenv by using getenv(name).
Examples	% Set and retrieve a new value for the environment variable TEMP:
	setenv('TEMP', 'C:\TEMP'); getenv('TEMP')
	% Append the Perl\bin folder to your system PATH variable:
16 1	INIX is a registered trademark of The Open Group in the United States and

16. UNIX is a registered trademark of The Open Group in the United States and other countries.

setenv('PATH', [getenv('PATH') ';D:\Perl\bin']);

See Also getenv, system, unix, dos, !

setfield

Purpose	Assign values to structure array field
Syntax	<pre>struct = setfield(struct,'field',value) struct = setfield(struct,{sIndx1,,sIndxM},'field',{fIndx1,</pre>
Description	<pre>struct = setfield(struct, 'field',value), where struct is a 1-by-1 structure, sets the contents of the specified field, equivalent to struct.field = value. If struct does not contain the specified field, the setfield function creates the field and assigns the specified value. Pass field references as strings.</pre>
	<pre>struct = setfield(struct,{sIndx1,,sIndxM},'field',{fIndx1,,fIndxN},value) sets the contents of the specified field, equivalent to struct(sIndx1,,sIndxM).field(fIndx1,,fIndxN) = value. The setfield function supports multiple sets of field and fIndx inputs. If structure struct or any of the fields is a nonscalar structure, the Indx inputs associated with that input are required. Otherwise, the Indx inputs are optional. If you specify a single colon operator for an index input, enclose it in single quotation marks: ':'.</pre>
Tips	• For most cases, add data to a structure array by indexing rather than using the setfield function. For more information, see "Indexing into a Struct Array" and "Creating Field Names Dynamically".
	• Call setfield to simplify references to structure arrays with nested fields, as shown in the Examples section.
Examples	<pre>Add values to a structure that contains nested fields: grades = []; level = 5; semester = 'Fall'; subject = 'Math'; student = 'John_Doe';</pre>

```
fieldnames = {semester subject student}
                     newGrades Doe = [85, 89, 76, 93, 85, 91, 68, 84, 95, 73];
                     grades = setfield(grades, {level}, ...
                                        fieldnames{:}, {10, 21:30}, ...
                                        newGrades Doe);
                     % View the new contents.
                     grades(level).(semester).(subject).(student)(10, 21:30)
                  Using the structure defined in the previous example, remove the tenth
                  row of the specified field:
                     grades = setfield(grades, {level}, fieldnames{:}, {10, ':'}, []);
See Also
                  getfield | fieldnames | isfield | orderfields | rmfield
How To
                  · "Guidelines for Naming Structure Fields"
                  • "Creating Field Names Dynamically"
                  • "Indexing into a Struct Array"
```

setinterpmethod

Purpose	Set default interpolation method for timeseries object
Syntax	<pre>ts = setinterpmethod(ts,Method) ts = setinterpmethod(ts,FHandle) ts = setinterpmethod(ts,InterpObj),</pre>
Description	<pre>ts = setinterpmethod(ts,Method) sets the default interpolation method for timeseries object ts, where Method is a string. Method in ts. Method is either 'linear' or 'zoh' (zero-order hold). For example: ts = timeseries(rand(100,1),1:100); ts = setinterpmethod(ts,'zoh'); ts = setinterpmethod(ts,FHandle) sets the default interpolation method for timeseries object ts, where FHandle is a function handle to the interpolation method defined by the function handle FHandle. For example: ts = timeseries(rand(100,1),1:100); myFuncHandle = @(new_Time,Time,Data)</pre>
	Note For FHandle, you must use three input arguments. The order of input arguments must be new_Time, Time, and Data. The single output argument must be the interpolated data only.
	ts = setinterpmethod(ts,InterpObj), where InterpObj is a tsdata.interpolation object that directly replaces the interpolation

ts = timeseries(rand(100,1),1:100);


object stored in ts. For example:

```
myFuncHandle = @(new_Time,Time,Data)...
interp1(Time,Data,new_Time,...
'linear','extrap');
myInterpObj = tsdata.interpolation(myFuncHandle);
ts = setinterpmethod(ts,myInterpObj);
This method is case sensitive.
```

See Also getinterpmethod, timeseries, tsprops


setpixelposition

Purpose	Set component position in pixels
Syntax	<pre>setpixelposition(handle,position) setpixelposition(handle,position,recursive)</pre>
Description	<pre>setpixelposition(handle,position) sets the position of the component specified by handle, to the specified position relative to its parent. position is a four-element vector that specifies the location and size of the component: [pixels from left, pixels from bottom, pixels across, pixels high].</pre>
	setpixelposition(handle,position,recursive) sets the position as above. If Boolean recursive is true, the position is set relative to the parent figure of handle.
Example	<pre>This example first creates a push button within a panel. f = figure('Position',[300 300 300 200]); p = uipanel('Position',[.2 .2 .6 .6]); h1 = uicontrol(p,'Style','PushButton','Units','normalized', 'String','Push Button','Position',[.1 .1 .5 .2]);</pre>



The example then retrieves the position of the push button and changes its position with respect to the panel.

```
pos1 = getpixelposition(h1);
setpixelposition(h1,pos1 + [10 10 25 25]);
```



See Also

getpixelposition, uicontrol, uipanel

Purpose	Set preference
Syntax	<pre>setpref('group','pref',val) setpref('group',{'pref1','pref2',,'prefn'},{val1,val2,, valn})</pre>
Description	<pre>setpref('group', 'pref', val) sets the preference specified by group and pref to the value val. Setting a preference that does not yet exist causes it to be created. group labels a related collection of preferences. You can choose any</pre>
	name that is a legal variable name, and is descriptive enough to be unique, e.g., 'MathWorks_GUIDE_ApplicationPrefs'. The input argument pref identifies an individual preference in that group, and must be a legal variable name.
	<pre>setpref('group',{'pref1','pref2',,'prefn'},{val1,val2,,valn}) sets each preference specified in the cell array of names to the corresponding value.</pre>
	Note Preference values are persistent and maintain their values between MATLAB sessions. Where they are stored is system dependent.
Examples	addpref('mytoolbox','version','0.0') setpref('mytoolbox','version','1.0') getpref('mytoolbox','version')
	ans = 1.0
See Also	addpref, getpref, ispref, rmpref, uigetpref, uisetpref

Purpose	Set string flag
	Note setstr will be removed in a future version. Use char instead.
Description	This MATLAB 4 function has been renamed char in MATLAB 5.

Purpose	Make subIFD specified by byte offset current IFD
Syntax	tiffobj.setSubDirectory(offset)
Description	tiffobj.setSubDirectory(offset) sets the subimage file directory (subIFD) specified by offset the current IFD. The offset value is given in bytes. Use this method when you want to access subIFDs linked through the SubIFD tag.
Examples	Open a TIFF file and read the value of the SubIFD tag in the current IFD. The SubIFD tag contains byte offsets that specify the location of subIFDs in the IFD. Replace myfile.tif with the name of a TIFF file on your MATLAB path. The TIFF file should contain subIFDs.
	<pre>t = Tiff('myfile.tif','r'); % % Read the value of the SubIFD tag to get subdirectory offsets. offsets = t.getTag('SubIFD'); % % Set one of the subdirectories (if more than one) as the current d t.setSubDirectory(offsets(1));</pre>
References	This method corresponds to the TIFFSetSubDirectory function in the LibTIFF C API. To use this method, you must be familiar with LibTIFF version 3.7.1, as well as the TIFF specification and technical notes. View this documentation at LibTIFF - TIFF Library and Utilities.
See Also	Tiff.setDirectory
Tutorials	"Exporting Image Data and Metadata to TIFF Files""Reading Image Data and Metadata from TIFF Files"

Tiff.setTag

Purpose	Set value of tag
Syntax	tiffobj.setTag(tagId,tagValue) tiffobj.setTag(tagStruct)
Description	tiffobj.setTag(tagId,tagValue) sets the value of the TIFF tag specified by tagId to the value specified by tagValue. You can specify tagId as a character string ('ImageWidth') or using the numeric tag identifier defined by the TIFF specification (256). To see a list of all the tags with their numeric identifiers, view the value of the Tiff object TagID property. Use the TagID property to specify the value of a tag. For example, Tiff.TagID.ImageWidth is equivalent to the tag's numeric identifier.
	tiffobj.setTag(tagStruct) sets the values of all of the tags with name/value fields in tagStruct. The names of fields in tagstruct must be the name of TIFF tags.
Examples	Create a structure with fields named after TIFF tags and assign values to the fields. Pass this structure to the setTag method to set the values of these tags. Replace myfile.tif with the name of a TIFF file on your MATLAB path.
	<pre>t = Tiff('myfile.tif', 'r+');</pre>
	<pre>tagStruct.ImageWidth = 1600; tagStruct.ImageLength = 3200; tagStruct.Photometric = Tiff.Photometric.RGB; tagStruct.BitPerSample = 8; tagStruct.SamplesPerPixel = 3; tagStruct.TileWidth = 160; tagStruct.TileLength = 320; tagStruct.PlanarConfiguration = Tiff.PlanarConfiguration.Chunky; tagStruct.Software = 'MATLAB'; t.setTag(tagStruct);</pre>

References	This method corresponds to the TIFFSetField function in the LibTIFF C API. To use this method, you must be familiar with LibTIFF version 3.7.1, as well as the TIFF specification and technical notes. View this documentation at LibTIFF - TIFF Library and Utilities.
See Also	Tiff.getTag
Tutorials	• "Exporting Image Data and Metadata to TIFF Files"

• "Reading Image Data and Metadata from TIFF Files"

settimeseriesnames

Purpose	Change name of timeseries object in tscollection
Syntax	<pre>tsc = settimeseriesnames(tsc,old,new)</pre>
Description	<pre>tsc = settimeseriesnames(tsc,old,new) replaces the old name of timeseries object with the new name in tsc.</pre>
See Also	tscollection

Purpose	Find set exclusive OR of two vectors
Syntax	c = setxor(A, B) c = setxor(A, B, 'rows') [c, ia, ib] = setxor()
Description	c = setxor(A, B) returns the values that are not in the intersection of A and B. Inputs A and B can be numeric or character vectors or cell arrays of strings. The resulting vector is sorted.
	c = setxor(A, B, 'rows'), when A and B are matrices with the same number of columns, returns the rows that are not in the intersection of A and B.
	<pre>[c, ia, ib] = setxor() also returns index vectors ia and ib such that c is a sorted combination of the elements c = a(ia) and c = b(ib) or, for row combinations, c = a(ia,:) and c = b(ib,:).</pre>
Examples	a = [-1 0 1 Inf -Inf NaN]; b = [-2 pi 0 Inf]; c = setxor(a, b)
	c = -Inf -2.0000 -1.0000 1.0000 3.1416 NaN
See Also	intersect, ismember, issorted, setdiff, union, unique

shading

Purpose	Set color shading properties				
Syntax	<pre>shading flat shading faceted shading interp shading(axes_handle,)</pre>				
Description	The shading function controls the color shading of surface and patch graphics objects.				
	shading flat each mesh line segment and face has a constant color determined by the color value at the endpoint of the segment or the corner of the face that has the smallest index or indices.				
	shading faceted flat shading with superimposed black mesh lines. This is the default shading mode.				
	shading interp varies the color in each line segment and face by interpolating the colormap index or true color value across the line or face.				
	<pre>shading(axes_handle,) applies the shading type to the objects in the axes specified by axes_handle, instead of the current axes.</pre>				
Examples	Compare a flat, faceted, and interpolated-shaded sphere.				
	<pre>subplot(3,1,1) sphere(16) axis square shading flat title('Flat Shading') subplot(3,1,2) sphere(16) axis square shading faceted title('Faceted Shading') subplot(3,1,3)</pre>				

	sphere(16) axis square shading interp title('Interpolated Shading')
Algorithm	shading sets the EdgeColor and FaceColor properties of all surface and patch graphics objects in the current axes. shading sets the appropriate values, depending on whether the surface or patch objects represent meshes or solid surfaces.
See Also	fill, fill3, hidden, light, lighting, mesh, patch, pcolor, surf The EdgeColor and FaceColor properties for patch and surface graphics objects.
	"Color Operations" on page 1-108 for related functions


Purpose	Show most recent graph window		
Syntax	shg		
Description	shg makes the current figure visible and raises it above all other figures on the screen. This is identical to using the command figure(gca).		
See Also	figure, gca, gcf		

Purpose	Shift dimensions			
Syntax	B = shiftdim(X,n) [B,nshifts] = shiftdim(X)			
Description	B = shiftdim(X,n) shifts the dimensions of X by n. When n is positive, shiftdim shifts the dimensions to the left and wraps the n leading dimensions to the end. When n is negative, shiftdim shifts the dimensions to the right and pads with singletons.			
	<pre>[B,nshifts] = shiftdim(X) returns the array B with the same number of elements as X but with any leading singleton dimensions removed. A singleton dimension is any dimension for which size(A,dim) = 1. nshifts is the number of dimensions that are removed.</pre>			
	If X is a scalar, shiftdim has no effect.			
Examples	The shiftdim command is handy for creating functions that, like sum or diff, work along the first nonsingleton dimension.			
	a = rand(1,1,3,1,2); [b,n] = shiftdim(a); % b is 3-by-1-by-2 and n is 2. c = shiftdim(b,-n); % c == a. d = shiftdim(a,3); % d is 1-by-2-by-1-by-1-by-3.			
See Also	circshift, reshape, squeeze, permute, ipermute			

showplottool

Purpose

Show or hide figure plot tool



GUI
AlternativesClick the larger Plotting Tools icon on the figure toolbar to
collectively enable plotting tools, and the smaller icon to collectively
disable them. Individually select the Figure Palette, Plot Browser,
and Property Editor tools from the figure's View menu. For details,
see "Plotting Tools — Interactive Plotting" in the MATLAB Graphics
documentation.Syntaxshowplottool('tool')
showplottool('on', 'tool')

snowplottool('on','tool')
showplottool('off','tool')
showplottool('toggle','tool')
showplottool(figure handle,...)

Description showplottool('tool') shows the specified plot tool on the current figure. tool can be one of the following strings:

- figurepalette
- plotbrowser
- propertyeditor

showplottool('on','tool') shows the specified plot tool on the current figure.

showplottool('off','tool') hides the specified plot tool on the current figure.

showplottool('toggle','tool') toggles the visibility of the specified
plot tool on the current figure.

 $showplottool(figure_handle,...)$ operates on the specified figure instead of the current figure.

Note When you dock, undock, resize, or reposition a plotting tool and then close it, it will still be configured as you left it the next time you open it. There is no command to reset plotting tools to their original, default locations.

See Also figurepalette, plotbrowser, plottools, propertyeditor


shrinkfaces


Purpose	Reduce size of patch faces		
Syntax	<pre>shrinkfaces(p,sf) nfv = shrinkfaces(p,sf) nfv = shrinkfaces(fv,sf) shrinkfaces(p) nfv = shrinkfaces(f,v,sf) [nf,nv] = shrinkfaces()</pre>		
Description	<pre>shrinkfaces(p,sf) shrinks the area of the faces in patch p to shrink factor sf. A shrink factor of 0.6 shrinks each face to 60% of its original area. If the patch contains shared vertices, the MATLAB software creates nonshared vertices before performing the face-area reduction.</pre>		
	<pre>nfv = shrinkfaces(p,sf) returns the face and vertex data in the struct nfv, but does not set the Faces and Vertices properties of patch p.</pre>		
	nfv = shrinkfaces(fv, sf) uses the face and vertex data from the struct fv .		
	<pre>shrinkfaces(p) and shrinkfaces(fv) (without specifying a shrink factor) assume a shrink factor of 0.3.</pre>		
	nfv = shrinkfaces(f,v,sf) uses the face and vertex data from the arrays f and v.		
	<pre>[nf,nv] = shrinkfaces() returns the face and vertex data in two separate arrays instead of a struct.</pre>		
Examples	This example uses the flow data set, which represents the speed profile of a submerged jet within an infinite tank (type help flow for more information). Two isosurfaces provide a before and after view of the effects of shrinking the face size.		
	• First reducevolume samples the flow data at every other point and then isosurface generates the faces and vertices data.		

- The patch command accepts the face/vertex struct and draws the first (p1) isosurface.
- Use the daspect, view, and axis commands to set up the view and then add a title.
- The shrinkfaces command modifies the face/vertex data and passes it directly to patch.

```
[x,y,z,v] = flow;
[x,y,z,v] = reducevolume(x,y,z,v,2);
fv = isosurface(x,y,z,v,-3);
p1 = patch(fv);
set(p1,'FaceColor','red','EdgeColor',[.5,.5,.5]);
daspect([1 1 1]); view(3); axis tight
title('Original')
figure
p2 = patch(shrinkfaces(fv,.3));
set(p2,'FaceColor','red','EdgeColor',[.5,.5,.5]);
daspect([1 1 1]); view(3); axis tight
title('After Shrinking')
```

shrinkfaces






See Also isosurface, patch, reducevolume, daspect, view, axis "Volume Visualization" on page 1-111 for related functions

sign

Purpose	Signum function			
Syntax	Y = sign(X)			
Description	Y = sign(X) returns an array Y the same size as X, where each element of Y is:			
	• 1 if the corresponding element of X is greater than zero			
	• 0 if the corresponding element of X equals zero			
	- 1 if the corresponding element of \boldsymbol{X} is less than zero			
	For nonzero complex X, $sign(X) = X./abs(X)$.			
See Also	abs, conj, imag, real			

Purpose	Sine of argument in radians		
Syntax	Y = sin(X)		
Description	Y = sin(X) returns the circular sine of the elements of X. The sin function operates element-wise on arrays. The function's domains and ranges include complex values. All angles are in radians.		
Definitions	The sine of an angle is:		
	$\sin(x) = \frac{e^{ix} - e^{-ix}}{2i}$ For complex x:		
	$\sin(x+iy) = \sin(x)\cosh(y) + i\cos(x)\sinh(y)$		
Examples	Graph the sine function over the domain $-\pi \leq x \leq \pi$.		
	<pre>x = -pi:0.01:pi; plot(x,sin(x)), grid on</pre>		



References sin uses FDLIBM, which was developed at SunSoft, a Sun Microsystems, Inc. business, by Kwok C. Ng, and others. For information about FDLIBM, see http://www.netlib.org.

See Also sind

Purpose	Sine of argument in degrees		
Syntax	Y = sind(X)		
Description	Y = sind(X) is the sine of the elements of X, expressed in degrees.		
Examples	For integers n, sind(n*180) is exactly zero, whereas sin(n*pi) reflect the accuracy of the floating point value of pi.		
	<pre>isequal(sind(180),sin(pi))</pre>		
See Also	sin		

single

Purpose	Convert to single precision				
Syntax	B = single(A)				
Description	B = single(A) converts the matrix A to single precision, returning that value in B. A can be any numeric object (such as a double). If A is already single precision, single has no effect. Single-precision quantities require less storage than double-precision quantities, but have less precision and a smaller range.				
	The single class is primarily meant to be used to store single-precision values. Hence most operations that manipulate arrays without changing their elements are defined. Examples are reshape, size, the relational operators, subscripted assignment, and subscripted reference			anipulate arrays without xamples are reshape, size, the	
	You can define your own methods for the single class by placing the appropriately named method in an @single folder within a folder on your path.				
Examples	<pre>a = magic(4); b = single(a);</pre>				
	whos Name	Size	Bytes	Class	
	a b	4x4 4x4	128 64	double array single array	
See Also	double				

Purpose	Hyperbolic sine of argument in radians		
Syntax	Y = sinh(X)		
Description	The sinh function operates element-wise on arrays. The function's domains and ranges include complex values. All angles are in radians. Y = sinh(X) returns the hyperbolic sine of the elements of X.		
Examples	Graph the hyperbolic sine function over the domain $-5 \le x \le 5$. x = -5:0.01:5; plot(x,sinh(x)), grid on 0 0 -20 -40		
Definition	-60 -80 -5 The hyperbolic sine can be defined as		

$$\sinh(z) = \frac{e^z - e^{-z}}{2}$$

Algorithm	<pre>sinh uses FDLIBM, which was developed at SunSoft, a Sun Microsystems, Inc. business, by Kwok C. Ng, and others. For information about FDLIBM, see http://www.netlib.org.</pre>
See Also	sin, sind, asin, asinh, asind

D				
Purpose	Array dimensions	Array dimensions		
Syntax	<pre>d = size(X) [m,n] = size(X) m = size(X,dim) [d1,d2,d3,,dn] = size(X),</pre>			
Description	<pre>d = size(X) returns the sizes of each dimension of array X in a vector d with ndims(X) elements. If X is a scalar, which MATLAB software regards as a 1-by-1 array, size(X) returns the vector [1 1]. [m,n] = size(X) returns the size of matrix X in separate variables m and n. m = size(X,dim) returns the size of the dimension of X specified by scalar dim. [d1,d2,d3,,dn] = size(X), for n > 1, returns the sizes of the dimensions of the array X in the variables d1,d2,d3,,dn, provided the number of output arguments n equals ndims(X). If n does not equal ndims(X), the following exceptions hold:</pre>			
	n < ndims(X)	di equals the size of the ith dimension of X for $1 \le i < n$, but dn equals the product of the sizes of the remaining dimensions of X, that is, dimensions n through ndims(X).		
	n > ndims(X)	size returns ones in the "extra" variables, that is, those corresponding to $ndims(X)+1$ through n.		
	Note For a Java array, size returns the length of the Java an number of rows. The number of columns is always 1. For a Ja of arrays, the result describes only the top level array.			
Examples	Example 1	cond dimension of rand $(2, 3, 4)$ is 3		

The size of the second dimension of rand(2,3,4) is 3.

Here the size is output as a single vector.

Here the size of each dimension is assigned to a separate variable.

Example 2

If X = ones(3,4,5), then [d1,d2,d3] = size(X) d1 = d2 = d3 = 34 5

But when the number of output variables is less than ndims(X):

```
[d1,d2] = size(X)
d1 = d2 =
3 20
```

The "extra" dimensions are collapsed into a single product.

If n > ndims(X), the "extra" variables all represent singleton dimensions:

 $\begin{bmatrix} d1, d2, d3, d4, d5, d6 \end{bmatrix} = size(X)$ $d1 = d2 = d3 = \\ 3 & 4 & 5$ $d4 = d5 = d6 = \\ 1 & 1 & 1$

See Also

exist, length, numel, whos

size (Map)

Purpose	size of containers.Map object
Syntax	d = size(M) d = size(M, dim) [d1, d2,, dn] = size(M)
Description	<pre>d = size(M) returns the number of key-value pairs in dimensions 1 and 2 of map M. Output d is a two-element row vector [n,1], where n is the number of key-value pairs.</pre>
	d = size(M, dim) returns the number of key-value pairs if dim is 1, and otherwise returns 1.
	$[d1, d2, \ldots, dn] = size(M)$ returns $[n, 1, \ldots, 1]$ where n is the number of key-value pairs in map M.
	Read more about Map Containers in the MATLAB Programming Fundamentals documentation.
Examples	Create a Map object containing the names of several US states and the capital city of each:
	US_Capitals = containers.Map({'Arizona', 'Nebraska', 'Nevada', 'New York', 'Georgia', 'Alaska', 'Vermont', 'Oregon'}, {'Phoenix', 'Lincoln', 'Carson City', 'Albany', 'Atlanta', 'Juneau', 'Montpelier', 'Salem'})
	Get the dimensions of the Map object array:
	size(US_Capitals) ans = 8 1
	Use the map to find the capital of one of these states:
	state = 'Georgia'; sprintf(' The capital of %s is %s', state, US_Capitals(state))

ans =						
The	capital	of	Georgia	is	Atlanta	

See Also containers.Map, keys(Map), values(Map), length(Map), isKey(Map), remove(Map), handle

size (serial)

Purpose	Size of serial port object array
Syntax	d = size(obj) [m,n] = size(obj) [m1,m2,m3,,mn] = size(obj) m = size(obj,dim)
Description	d = size(obj) returns the two-element row vector d containing the number of rows and columns in the serial port object, obj.
	[m,n] = size(obj) returns the number of rows, m and columns, n in separate output variables.
	<pre>[m1,m2,m3,,mn] = size(obj) returns the length of the first n dimensions of obj.</pre>
	<pre>m = size(obj,dim) returns the length of the dimension specified by the scalar dim. For example, size(obj,1) returns the number of rows.</pre>
See Also	Functions
	length

Purpose	Size of timeseries object
Syntax	<pre>size(ts)</pre>
Description	<pre>size(ts) returns [n 1], where n is the length of the time vector for timeseries object ts.</pre>
Remarks	If you want the size of the whole data set, use the following syntax:
	<pre>size(ts.data)</pre>
	If you want the size of each data sample, use the following syntax:
	getdatasamplesize(ts)
See Also	getdatasamplesize, isempty (timeseries), length (timeseries)

TriRep.size

Purpose	Size of triangulation matrix
Syntax	size(TR)
Description	<pre>size(TR) provides size information for a triangulation matrix. The matrix is of size mtri-by-nv, where mtri is the number of simplices and nv is the number of vertices per simplex (triangle/tetrahedron, etc).</pre>
Input Arguments	TR Triangulation matrix
Definitions	A simplex is a triangle/tetrahedron or higher-dimensional equivalent.
See Also	size

Purpose	Size of tscollection object
Syntax	<pre>size(tsc)</pre>
Description	size(tsc) returns $[n m]$, where n is the length of the time vector and m is the number of tscollection members.
See Also	length (tscollection), isempty (tscollection), tscollection

slice

Purpose

Volumetric slice plot



GUI Alternatives

To graph selected variables, use the Plot Selector **Plot(t,y)** in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in *plot edit* mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.

Syntax slice(V,sx,sy,sz)
slice(X,Y,Z,V,sx,sy,sz)
slice(V,XI,YI,ZI)
slice(X,Y,Z,V,XI,YI,ZI)
slice(...,'method')
slice(axes_handle,...)
h = slice(...)


Description slice displays orthogonal slice planes through volumetric data.

slice(V,sx,sy,sz) draws slices along the x, y, z directions in the
volume V at the points in the vectors sx, sy, and sz. V is an m-by-n-by-p
volume array containing data values at the default location X = 1:n,
Y = 1:m, Z = 1:p. Each element in the vectors sx, sy, and sz defines
a slice plane in the x-, y-, or z-axis direction.

slice(X,Y,Z,V,sx,sy,sz) draws slices of the volume V. X, Y, and Z are three-dimensional arrays specifying the coordinates for V. X, Y, and Z must be monotonic and orthogonally spaced (as if produced by the function meshgrid). The color at each point is determined by 3-D interpolation into the volume V.

slice(V,XI,YI,ZI) draws data in the volume V for the slices defined by XI, YI, and ZI. XI, YI, and ZI are matrices that define a surface,

	and the volume is evaluated at the surface points. XI, YI, and ZI must all be the same size.
	<pre>slice(X,Y,Z,V,XI,YI,ZI) draws slices through the volume V along the surface defined by the arrays XI, YI, ZI.</pre>
	<pre>slice(,'method') specifies the interpolation method. 'method' is 'linear', 'cubic', or 'nearest'.</pre>
	• linear specifies trilinear interpolation (the default).
	• cubic specifies tricubic interpolation.
	 nearest specifies nearest-neighbor interpolation.
	<pre>slice(axes_handle,) plots into the axes with the handle axes_handle instead of into the current axes object (gca). The axes clim property is set to span the finite values of V.</pre>
	<pre>h = slice() returns a vector of handles to surface graphics objects.</pre>
Remarks	The color drawn at each point is determined by interpolation into the volume V.
Examples	Visualize the function
	$v = xe^{\left(-x^2 - y^2 - z^2\right)}$
	over the range $-2 \le x \le 2, -2 \le y \le 2, -2 \le z \le 2$:
	<pre>[x,y,z] = meshgrid(-2:.2:2,-2:.25:2,-2:.16:2); v = x.*exp(-x.^2-y.^2-z.^2); xslice = [-1.2,.8,2]; yslice = 2; zslice = [-2,0]; slice(x,y,z,v,xslice,yslice,zslice) colormap hsv</pre>



x-axis sheet at -1.2, .0, a

Slicing At Arbitrary Angles

You can also create slices that are oriented in arbitrary planes. To do this,


- Create a slice surface in the domain of the volume (surf, linspace).
- Orient this surface with respect to the axes (rotate).
- Get the XData, YData, and ZData of the surface (get).
- Use this data to draw the slice plane within the volume.

For example, these statements slice the volume in the first example with a rotated plane. Placing these commands within a for loop "passes" the plane through the volume along the *z*-axis.

```
for i = -2:.5:2
hsp = surf(linspace(-2,2,20),linspace(-2,2,20),zeros(20)+i);
```

```
rotate(hsp,[1,-1,1],30)
xd = get(hsp,'XData');
yd = get(hsp,'YData');
zd = get(hsp,'ZData');
delete(hsp)
slice(x,y,z,v,[-2,2],2,-2) % Draw some volume boundaries
hold on
slice(x,y,z,v,xd,yd,zd)
hold off
axis tight
view(-5,10)
drawnow
end
```

The following picture illustrates three positions of the same slice surface as it passes through the volume.




Slicing with a Nonplanar Surface

You can slice the volume with any surface. This example probes the volume created in the previous example by passing a spherical slice surface through the volume.

```
[xsp, ysp, zsp] = sphere;
slice(x,y,z,v,[-2,2],2,-2) % Draw some volume boundaries
for i = -3:.2:3
hsp = surface(xsp+i,ysp,zsp);
rotate(hsp,[1 0 0],90)
xd = get(hsp,'XData');
yd = get(hsp, 'YData');
zd = get(hsp,'ZData');
delete(hsp)
hold on
hslicer = slice(x,y,z,v,xd,yd,zd);
axis tight
xlim([-3,3])
view(-10,35)
drawnow
delete(hslicer)
hold off
end
```


The following picture illustrates three positions of the spherical slice surface as it passes through the volume.



See Also interp3, meshgrid "Volume Visualization" on page 1-111 for related functions Exploring Volumes with Slice Planes for more examples

smooth3

Purpose	Smooth 3-D data
Syntax	
Description	W = smooth3(V) smooths the input data V and returns the smoothed data in W.
	W = smooth3(V,'filter') filter determines the convolution kernel and can be the strings
	• 'gaussian'
	• 'box' (default)
	W = smooth3(V, ' <i>filter</i> ', size) sets the size of the convolution kernel (default is [3 3 3]). If size is scalar, then size is interpreted as [size, size, size].
	W = smooth3(V,' <i>filter</i> ',size,sd) sets an attribute of the convolution kernel. When <i>filter</i> is gaussian, sd is the standard deviation (default is .65).
Examples	This example smooths some random 3-D data and then creates an isosurface with end caps.
	<pre>rand('seed',0) data = rand(10,10,10); data = smooth3(data,'box',5); p1 = patch(isosurface(data,.5),</pre>




See Also isocaps, isonormals, isosurface, patch "Volume Visualization" on page 1-111 for related functions See Displaying an Isosurface for another example.


snapnow

Purpose	Force snapshot of image for inclusion in published document				
GUI Alternative	As an alternative to snapnow, open a MATLAB code file and select Cell > Insert Text Markup > Force Snapshot to insert the snapnow command into the file.				
Syntax	snapnow				
Description	The snapnow command forces a snapshot of the image or plot that the code has most recently generated for presentation in a published document. The output appears in the published document at the end of the cell that contains the snapnow command. When used outside the context of publishing a file, snapnow has the same behavior as drawnow. That is, if you run a file that contains the snapnow command, the MATLAB software interprets it as though it were a drawnow command.				
Example	<pre>This example demonstrates the difference between publishing code that contains the snapnow command and running that code. The first image shows the results of publishing the code and the second image shows the results of running the code.</pre> Suppose you have a file that contains the following code: %% Scale magic Data and %% Display as Image: for i=1:3 i imagesc(magic(i)) snapnow end				

When you publish the code to HTML, the published document contains a title, a table of contents, the commented text, the code, and each of the three images produced by the for loop, along with a display of the value of i corresponding to each image. (In the published document shown, the size of the images have been reduced.)



When you run the code, a single Figure window opens and MATLAB updates the image within this window as it evaluates each iteration of the for loop. (Concurrently, the Command Window displays the value of i.) Each successive image replaces the one that preceded it, so that the Figure window appears as follows when the code evaluation completes.



See Also drawnow

"Forcing a Snapshot of Output in MATLAB Files for Publishing"

Purpose	Sort array	elements in	ascending or	descending order
I UI PUSC	buit array	elements m	ascenting of	uescentuing or uer

Syntax B = sort(A)
B = sort(A,dim)
B = sort(...,mode)
[B,IX] = sort(A,...)

Description B = sort (A) sorts the elements along different dimensions of an array, and arranges those elements in ascending order.

lf A is a	sort(A)				
Vector	Sorts the elements of A.				
Matrix	Sorts each column of A.				
Multidimensional array	Sorts A along the first non-singleton dimension, and returns an array of sorted vectors.				
Cell array of strings	Sorts the strings in ascending ASCII dictionary order, and returns a vector cell array of strings. You cannot use the dim or mode options with a cell array.				

Integer, floating-point, logical, and character arrays are permitted. Floating-point arrays can be complex. For elements of A with identical values, the order of these elements is preserved in the sorted list. When A is complex, the elements are sorted by magnitude, i.e., abs(A), and where magnitudes are equal, further sorted by phase angle, i.e., angle(A), on the interval $[-\pi, \pi]$. If A includes any NaN elements, sort places these at the high end.

B = sort(A, dim) sorts the elements along the dimension of A specified by a scalar dim.

B = sort(...,mode) sorts the elements in the specified direction, depending on the value of mode. 'ascend' Ascending order (default)

'descend' Descending order

[B,IX] = sort(A,...) also returns an array of indices IX, where size(IX) == size(A). If A is a vector, B = A(IX). If A is an m-by-n matrix, then each column of IX is a permutation vector of the corresponding column of A, such that

for j = 1:n
 B(:,j) = A(IX(:,j),j);
end

If A has repeated elements of equal value, the returned indices preserve the original ordering.

Sorting Complex Entries

If A has complex entries r and s, sort orders them according to the following rule: r appears before s in sort(A) if either of the following hold:

- abs(r) < abs(s)
- abs(r) = abs(s) and angle(r)<angle(s)

where $-\pi < angle(r) \leq \pi$

For example,

```
v = [1 -1 i -i];
angle(v)
ans =
0 3.1416 1.5708 -1.5708
sort(v)
ans =
```

0 - 1.0000i 1.0000 0 + 1.0000i -1.0000

Note sort uses a different rule for ordering complex numbers than do the relational operators. See the Relational Operators reference page for more information. For more information about how MATLAB software treats complex numbers, see "Numbers" in the *MATLAB Getting Started Guide*.

Examples Example 1

Sort horizontal vector A:

A = [78 23 10 100 45 5 6]; sort(A) ans = 5 6 10 23 45 78 100

Example 2

Sort matrix A in each dimension:

A = [3 7 5 0 4 2]; sort(A,1) ans = 0 4 2 3 7 5 sort(A,2) ans = 3 5 7 0 2 4

Sort it again, this time returning an array of indices for the result:

Example 3

Sort each column of matrix A in descending order:

```
A = [ 3 7 5
         6 8 3
        0 4 2 ];
  sort(A,1,'descend')
  ans =
        6
            8
                5
        3
                3
            7
        0
                2
            4
This is equivalent to
  sort(A, 'descend')
  ans =
        6
            8
                5
        3
                3
            7
        0
            4
                2
```

See Also

issorted, max, mean, median, min, sortrows, unique

sortrows

Sort rows in	ascen	ding ord	er				
B = sortro	ws(A,c)				
						ng order	. Argument A
elements ar	e sorte	d by mag	gnitude	e, and, v	wher <u>e</u> n	nagnitud	-
B = sortrows(A,column) sorts the matrix based on the columns specified in the vector column. If an element of column is positive, the MATLAB software sorts the corresponding column of matrix A in ascending order; if an element of column is negative, MATLAB sorts the corresponding column in descending order. For example, sortrows(A,[2 -3]) sorts the rows of A first in ascending order for the second column, and then by descending order for the third column.							
[B,index] = sortrows(A,) also returns an index vector index.							
If A is a column vector, then $B = A(index)$. If A is an m-by-n matrix, then $B = A(index,:)$.							
Start with a	ın arbit	trary ma	trix, A:				
A=floor A(1:4,1) A = 95 95 95	galle	ry('uni	formda	ta',[6			,3)=73
	B = sortro B = sortro [B,index] B = sortro must be eith For strings, elements ar further sort B = sortro specified in the MATLA in ascending sorts the con sortrows (A second colum [B,index] If A is a colu then B = A(Start with a A=floor(A(1:4,1)) A = 95 95	B = sortrows(A) B = sortrows(A, C [B, index] = sort B = sortrows(A) must be either a m For strings, this is elements are sorted further sorted by p B = sortrows(A, C specified in the vec the MATLAB softw in ascending order sorts the correspon sortrows(A, [2 -3 second column, and [B, index] = sort If A is a column vec then B = A(index) Start with an arbit A=floor(galle A(1:4,1)=95; A = 95 45 95 7 95 7	<pre>B = sortrows(A) B = sortrows(A, column) [B, index] = sortrows(A, B = sortrows(A) sorts the must be either a matrix or For strings, this is the family elements are sorted by mage further sorted by phase and B = sortrows(A, column) specified in the vector coluct the MATLAB software sort in ascending order; if an el sorts the corresponding col sortrows(A, [2 -3]) sorts second column, and then by [B, index] = sortrows(A, If A is a column vector, the then B = A(index,:). Start with an arbitrary mate A=floor(gallery('uni A(1:4,1)=95; A(5:6, A = 95 45 92 95 7 73 95 7 73</pre>	<pre>B = sortrows(A, column) [B, index] = sortrows(A,) B = sortrows(A) sorts the rows of must be either a matrix or a colum For strings, this is the familiar did elements are sorted by magnitude further sorted by phase angle on t B = sortrows(A, column) sorts t specified in the vector column. If the MATLAB software sorts the co in ascending order; if an element sorts the corresponding column in sortrows(A,[2 -3]) sorts the row second column, and then by desce [B, index] = sortrows(A,) a If A is a column vector, then B = A then B = A(index,:). Start with an arbitrary matrix, A: A=floor(gallery('uniformda A(1:4,1)=95; A(5:6,1)=76; A = 95 45 92 41 95 7 73 89 95 7 73 5 </pre>	<pre>B = sortrows(A) B = sortrows(A, column) [B, index] = sortrows(A,) B = sortrows(A) sorts the rows of A in a must be either a matrix or a column vect For strings, this is the familiar dictionary elements are sorted by magnitude, and, v further sorted by phase angle on the inte B = sortrows(A, column) sorts the matrix specified in the vector column. If an element the MATLAB software sorts the corresponding order; if an element of colu- sorts the corresponding column in descer sortrows(A, [2 -3]) sorts the rows of A second column, and then by descending on [B, index] = sortrows(A,) also retuined then B = A(index, :). Start with an arbitrary matrix, A: A=floor(gallery('uniformdata', [6 A(1:4,1)=95; A(5:6,1)=76; A(2: A = 95 45 92 41 13 95 7 73 89 20 95 7 73 5 19</pre>	<pre>B = sortrows(A) B = sortrows(A,column) [B,index] = sortrows(A,) B = sortrows(A) sorts the rows of A in ascendin must be either a matrix or a column vector. For strings, this is the familiar dictionary sort. We elements are sorted by magnitude, and, where m further sorted by phase angle on the interval [-7] B = sortrows(A,column) sorts the matrix base specified in the vector column. If an element of of the MATLAB software sorts the corresponding of in ascending order; if an element of column is not sorts the corresponding column in descending or sortrows(A,[2 -3]) sorts the rows of A first in second column, and then by descending order for [B,index] = sortrows(A,) also returns an If A is a column vector, then B = A(index). If A then B = A(index,:). Start with an arbitrary matrix, A: A=floor(gallery('uniformdata',[6 7],0) A(1:4,1)=95; A(5:6,1)=76; A(2:4,2)=7 A = 95 45 92 41 13 1 95 7 73 89 20 74 95 7 73 5 19 44</pre>	$B = \text{sortrows}(A)$ $B = \text{sortrows}(A, \text{column})$ $[B, \text{index}] = \text{sortrows}(A, \dots)$ $B = \text{sortrows}(A) \text{ sorts the rows of A in ascending order must be either a matrix or a column vector.}$ For strings, this is the familiar dictionary sort. When A selements are sorted by magnitude, and, where magnitude further sorted by phase angle on the interval $[-\pi, \pi]$. $B = \text{sortrows}(A, \text{column}) sorts the matrix based on the specified in the vector column. If an element of column the MATLAB software sorts the corresponding column of a scending order; if an element of column is negative, sorts the corresponding column in descending order. For sortrows (A, [2 -3]) sorts the rows of A first in ascending second column, and then by descending order for the this [B, index] = sortrows (A,) also returns an index v If A is a column vector, then B = A(index). If A is an mathen B = A(index,:).$ Start with an arbitrary matrix, A: $A=floor(gallery('uniformdata', [6 7], 0)*100);$ $A(1:4,1)=95;$ $A(5:6,1)=76;$ $A(2:4,2)=7;$ $A(3, A)=$ $95 45 92 41 13 1 84 95 7 73 89 20 74 52 95 7 73 5 19 44 20$

When called with only a single input argument, sortrows bases the sort on the first column of the matrix. For any rows that have equal elements in a particular column, (e.g., A(1:4,1) for this matrix), sorting is based on the column immediately to the right, (A(1:4,2) in this case):

В =	= sortrows(A)						
В =							
	76	61	93	81	27	46	83
	76	79	91	0	19	41	1
	95	7	40	35	60	93	67
	95	7	73	5	19	44	20
	95	7	73	89	20	74	52
	95	45	92	41	13	1	84

When called with two input arguments, sortrows bases the sort entirely on the column specified in the second argument. Rows that have equal elements in the specified column, (e.g., A(2:4,:), if sorting matrix A by column 2) remain in their original order:

С	=	sort	sortrows(A,2)					
С	=							
		95	7	73	89	20	74	52
		95	7	73	5	19	44	20
		95	7	40	35	60	93	67
		95	45	92	41	13	1	84
		76	61	93	81	27	46	83
		76	79	91	0	19	41	1

This example specifies two columns to sort by: columns 1 and 7. This tells sortrows to sort by column 1 first, and then for any rows with equal values in column 1, to sort by column 7:

D =	sort	rows(A	,[1 7])			
D =	:						
	76	79	91	0	19	41	1
	76	61	93	81	27	46	83
	95	7	73	5	19	44	20
	95	7	73	89	20	74	52

95	7	40	35	60	93	67
95	45	92	41	13	1	84

Sort the matrix using the values in column 4 this time and in reverse order:

=	sort	sortrows(A,					
=							
	95	7	73	89	20	74	52
	76	61	93	81	27	46	83
	95	45	92	41	13	1	84
	95	7	40	35	60	93	67
	95	7	73	5	19	44	20
	76	79	91	0	19	41	1
		= 95 76 95 95 95	= 95 7 76 61 95 45 95 7 95 7	957737661939545929574095773	$= \begin{array}{cccccccccccccccccccccccccccccccccccc$	= 95 7 73 89 20 76 61 93 81 27 95 45 92 41 13 95 7 40 35 60 95 7 73 5 19	= 95 7 73 89 20 74 76 61 93 81 27 46 95 45 92 41 13 1 95 7 40 35 60 93 95 7 73 5 19 44



issorted, sort

Purpose	Convert matrix of signal data to sound
Syntax	<pre>sound(y,Fs) sound(y,Fs,bits)</pre>
Description	sound (y , Fs) sends audio signal y to the speaker at sample rate Fs . If you do not specify a sample rate, sound plays at 8192 Hz. For single-channel (mono) audio, y is an m -by-1 column vector, where m is the number of audio samples. If your system supports stereo playback, y can be an m -by-2 matrix, where the first column corresponds to the left channel, and the second column corresponds to the right channel. The sound function assumes that y contains floating-point numbers between -1 and 1, and clips values outside that range.
	<pre>sound(y,Fs,bits) specifies the bit depth (that is, the precision) of the sample values. The possible values for bit depth depend on the audio hardware available on your system. Most platforms support depths of 8 bits or 16 bits. If you do not specify bits, the sound function plays at an 8-bit depth.</pre>
Tips	• The sound function supports sound devices on all Windows and most UNIX platforms.
	• Most sound cards support sample rates between 5 kHz and 48 kHz. Specifying a sample rate outside this range produces unexpected results.
Examples	Load the demo file gong.mat, which contains sample data y and rate Fs , and listen to the audio:
	<pre>load gong.mat; sound(y, Fs);</pre>

Play an excerpt from Handel's "Hallelujah Chorus" at twice the recorded sample rate:

sound

	<pre>load handel.mat; sound(y, 2*Fs);</pre>
See Also	audioplayer soundsc wavread wavwrite
How To	 "Characteristics of Audio Files" "Playing Audio"

Purpose	Scale data and play as sound
Syntax	soundsc(y,Fs) soundsc(y,Fs,bits) soundsc(y,Fs,bits,range)
Description	soundsc(y,Fs) sends audio signal y to the speaker at sample rate Fs. If you do not specify a sample rate, soundsc plays at 8192 Hz. Like the sound function, soundsc assumes that y contains floating-point numbers. However, before playing the signal, soundsc scales the values to fit in the range from -1.0 to 1.0, so that the audio is played as loudly as possible without clipping.
	<pre>soundsc(y,Fs,bits) specifies the bit depth (that is, the precision) of the sample values. The possible values for bit depth depend on the audio hardware available on your system. Most platforms support depths of 8 bits or 16 bits. If you do not specify bits, the soundsc function plays at an 8-bit depth.</pre>
	<pre>soundsc(y,Fs,bits,range), where range is of the form [low high], maps the values in y between low and high to the full sound range. The default range is [min(y) max(y)]. Specifying Fs and bits is optional.</pre>
Tips	• The soundsc function supports sound devices on all Windows and most UNIX platforms.
	• Most sound cards support sample rates between 5 kHz and 48 kHz. Specifying a sample rate outside this range produces unexpected results.
See Also	audioplayer sound wavread wavwrite

spalloc

Purpose	Allocate space for sparse matrix
Syntax	S = spalloc(m,n,nzmax)
Description	<pre>S = spalloc(m,n,nzmax) creates an all zero sparse matrix S of size m-by-n with room to hold nzmax nonzeros. The matrix can then be generated column by column without requiring repeated storage allocation as the number of nonzeros grows. spalloc(m,n,nzmax) is shorthand for</pre>
	<pre>sparse([],[],[],m,n,nzmax)</pre>
Examples	To generate efficiently a sparse matrix that has an average of at most three nonzero elements per column S = spalloc(n,n,3*n);
	<pre>for j = 1:n S(:,j) = [zeros(n-3,1)' round(rand(3,1))']';end</pre>

Purpose	Create sparse matrix
Syntax	<pre>S = sparse(A) S = sparse(i,j,s,m,n,nzmax) S = sparse(i,j,s,m,n) S = sparse(i,j,s) S = sparse(m,n)</pre>
Description	The sparse function generates matrices in the MATLAB sparse storage organization.
	<pre>S = sparse(A) converts a full matrix to sparse form by squeezing out any zero elements. If S is already sparse, sparse(S) returns S.</pre>
	S = sparse(i, j, s, m, n, nzmax) uses vectors i, j, and s to generate an m-by-n sparse matrix such that $S(i(k), j(k)) = s(k)$, with space allocated for nzmax nonzeros. Vectors i, j, and s are all the same length. Any elements of s that are zero are ignored, along with the corresponding values of i and j. Any elements of s that have duplicate values of i and j are added together.
	Note If any value in i or j is larger than the maximum integer size, 2^31-1, then the sparse matrix cannot be constructed.
	To simplify this six-argument call, you can pass scalars for the argument s and one of the arguments i or j—in which case they are expanded so that i, j, and s all have the same length.
	S = sparse(i,j,s,m,n) uses nzmax = length(s).
	<pre>S = sparse(i,j,s) uses m = max(i) and n = max(j). The maxima are computed before any zeros in s are removed, so one of the rows of [i j s] might be [m n 0].</pre>
	<pre>S = sparse(m,n) abbreviates sparse([],[],[],m,n,0). This generates the ultimate sparse matrix, an m-by-n all zero matrix.</pre>

Remarks	All of the MATLAB built-in arithmetic, logical, and indexing operations can be applied to sparse matrices, or to mixtures of sparse and full matrices. Operations on sparse matrices return sparse matrices and operations on full matrices return full matrices.
	In most cases, operations on mixtures of sparse and full matrices return full matrices. The exceptions include situations where the result of a mixed operation is structurally sparse, for example, $A.*S$ is at least as sparse as S.
Examples	S = sparse(1:n,1:n,1) generates a sparse representation of the n-by-n identity matrix. The same S results from $S = sparse(eye(n,n))$, but this would also temporarily generate a full n-by-n matrix with most of its elements equal to zero.
	B = sparse(10000,10000,pi) is probably not very useful, but is legal and works; it sets up a 10000-by-10000 matrix with only one nonzero element. Don't try full(B); it requires 800 megabytes of storage.
	This dissects and then reassembles a sparse matrix:
	[i,j,s] = find(S); [m,n] = size(S); S = sparse(i,j,s,m,n);
	So does this, if the last row and column have nonzero entries:
	[i,j,s] = find(S); S = sparse(i,j,s);
See Also	diag, find, full, issparse, nnz, nonzeros, nzmax, spones, sprandn, sprandsym, spy
	The sparfun directory

```
Purpose
                   Form least squares augmented system
Syntax
                   S = spaugment(A,c)
                   S = spaugment(A)
Description
                   S = spaugment(A, c) creates the sparse, square, symmetric indefinite
                   matrix S = [c*I A; A' 0]. The matrix S is related to the least squares
                   problem
                      min norm(b - A*x)
                   by
                      r = b - A*x
                      S * [r/c; x] = [b; 0]
                   The optimum value of the residual scaling factor c, involves
                   \min(svd(A)) and norm(r), which are usually too expensive to compute.
                   S = spaugment(A) without a specified value of c, uses
                   max(max(abs(A)))/1000.
                   Note In previous versions of MATLAB product, the augmented matrix
                   was used by sparse linear equation solvers, \setminus and /, for nonsquare
                   problems. Now, MATLAB software performs a least squares solve using
                   the gr factorization of A instead.
```

See Also spparms

spconvert

Purpose	Import matrix from sparse matrix external format					
Syntax	S = spconvert(D)					
Description	spconvert is used to create sparse matrices from a simple sparse format easily produced by non-MATLAB sparse programs. spconvert is the second step in the process:					
	Load an ASCII data file containing [i,j,v] or [i,j,re,im] as rows into a MATLAB variable.					
	2 Convert that variable into a MATLAB sparse matrix.					
	S = spconvert(D) converts a matrix D with rows containing [i,j,s] or [i,j,r,s] to the corresponding sparse matrix. D must have an nnz or nnz+1 row and three or four columns. Three elements per row generate a real matrix and four elements per row generate a complex matrix. A row of the form [m n 0] or [m n 0 0] anywhere in D can be used to specify size(S). If D is already sparse, no conversion is done, so spconvert can be used after D is loaded from either a MAT-file or an ASCII file.					
Examples	Suppose the ASCII file uphill.dat contains					
	$\begin{array}{cccccccccccccccccccccccccccccccccccc$					

Then the statements

```
load uphill.dat
H = spconvert(uphill)
H =
   (1,1)
                1.0000
   (1,2)
                0.5000
   (2,2)
                0.3333
   (1,3)
                0.3333
   (2,3)
                0.2500
   (3,3)
                0.2000
   (1,4)
                0.2500
   (2,4)
                0.2000
   (3, 4)
                0.1667
   (4, 4)
                0.1429
```

recreate sparse(triu(hilb(4))), possibly with roundoff errors. In this case, the last line of the input file is not necessary because the earlier lines already specify that the matrix is at least 4-by-4.

spdiags

Purpose	Extract and create sparse band and diagonal matrices
Syntax	<pre>B = spdiags(A) [B,d] = spdiags(A) B = spdiags(A,d) A = spdiags(B,d,A) A = spdiags(B,d,m,n)</pre>
Description	The spdiags function generalizes the function diag. Four different operations, distinguished by the number of input arguments, are possible.
	 B = spdiags(A) extracts all nonzero diagonals from the m-by-n matrix A. B is a min(m,n)-by-p matrix whose columns are the p nonzero diagonals of A.
	[B,d] = spdiags(A) returns a vector d of length p, whose integer components specify the diagonals in A.
	B = spdiags(A,d) extracts the diagonals specified by d.
	A = spdiags(B,d,A) replaces the diagonals specified by d with the columns of B. The output is sparse.
	A = spdiags(B,d,m,n) creates an m-by-n sparse matrix by taking the columns of B and placing them along the diagonals specified by d.
	Note In this syntax, if a column of B is longer than the diagonal it is replacing, and $m \ge n$, spdiags takes elements of super-diagonals from the lower part of the column of B, and elements of sub-diagonals from the upper part of the column of B. However, if $m < n$, then super-diagonals are from the upper part of the column of B, and sub-diagonals from the lower part. (See "Example 5A" on page 2-3570 and "Example 5B" on page 2-3572, below).
Arguments	The spdiags function deals with three matrices, in various combinations, as both input and output.

А	An m-by-n matrix, usually (but not necessarily) sparse, with its nonzero or specified elements located on p diagonals.
В	A min(m,n)-by-p matrix, usually (but not necessarily) full,

- whose columns are the diagonals of A.
- d A vector of length p whose integer components specify the diagonals in A.


Roughly, A, B, and d are related by

for k = 1:p B(:,k) = diag(A,d(k))end

Some elements of B, corresponding to positions outside of A, are not defined by these loops. They are not referenced when B is input and are set to zero when B is output.

How the Diagonals of A are Listed in the Vector d

An m-by-n matrix A has m+n-1 diagonals. These are specified in the vector d using indices from -m+1 to n-1. For example, if A is 5-by-6, it has 10 diagonals, which are specified in the vector d using the indices -4, -3, ... 4, 5. The following diagram illustrates this for a vector of all ones.



Examples

Example 1

For the following matrix,

0060 3007	0 10 0 0 0 11 0; 7 0 12; 0 8 0;	•			
A =	, , , ,				
0	5	0	10	0	
0	0	6	0	11	
3	0	0	7	0	
1	4	0	0	8	
0	2	5	0	0	
e command					

the co

[B, d] =spdiags(A)

returns


В =

0	0	5	10
0	0	6	11
0	3	7	12
1	4	8	0
2	5	9	0


d =

- 3 -2 1 3

The columns of the first output B contain the nonzero diagonals of A. The second output d lists the indices of the nonzero diagonals of A, as shown in the following diagram. See "How the Diagonals of A are Listed in the Vector d" on page 2-3565.



Note that the longest nonzero diagonal in A is contained in column 3 of B. The other nonzero diagonals of A have extra zeros added to their corresponding columns in B, to give all columns of B the same length. For the nonzero diagonals below the main diagonal of A, extra zeros are added at the tops of columns. For the nonzero diagonals above the main diagonal of A, extra zeros are added at the bottoms of columns. This is illustrated by the following diagram.



Example 2

This example generates a sparse tridiagonal representation of the classic second difference operator on n points.

e = ones(n,1); A = spdiags([e -2*e e], -1:1, n, n)

Turn it into Wilkinson's test matrix (see gallery):

A = spdiags(abs(-(n-1)/2:(n-1)/2)',0,A)

Finally, recover the three diagonals:

B = spdiags(A)

Example 3

The second example is not square.

 $A = \begin{bmatrix} 11 & 0 & 13 & 0 \\ 0 & 22 & 0 & 24 \end{bmatrix}$

0	0	33	0
41	0	0	44
0	52	0	0
0	0	63	0
0	0	0	74]

```
Here m = 7, n = 4, and p = 3.
```

```
The statement [B,d] = spdiags(A) produces d = [-3 \ 0 \ 2]' and
```

В	=	[41	11	0
		52	22	0
		63	33	13
		74	44	24]

Conversely, with the above B and d, the expression $\mathtt{spdiags}(B,d,7,4)$ reproduces the original A.

Example 4

This example shows how spdiags creates the diagonals when the columns of B are longer than the diagonals they are replacing.

```
B = repmat((1:6)', [1 7])
B =
    1
      1
         1
            1
               1
                  1
                     1
    2
      2 2 2
               2
                  2
                     2
    3
      3 3 3 3 3 3
      4 4 4 4 4
    4
                    4
    5
      5
         5 5 5 5
                    5
    6
      6
         6
            6
               66
                     6
d = [-4 - 2 - 1 \ 0 \ 3 \ 4 \ 5];
A = spdiags(B,d,6,6);
full(A)
ans =
```

1	0	0	4	5	6
1	2	0	0	5	6
1	2	3	0	0	6
0	2	3	4	0	0
1	0	3	4	5	0
0	2	0	4	5	6

Example 5A

This example illustrates the use of the syntax A = spdiags(B,d,m,n), under three conditions:

- m is equal to n
- m is greater than n
- $\bullet\,$ m is less than n

The command used in this example is

 $A = full(spdiags(B, [-2 \ 0 \ 2], m, n))$

where B is the 5-by-3 matrix shown below. The resulting matrix A has dimensions m-by-n, and has nonzero diagonals at $[-2 \ 0 \ 2]$ (a sub-diagonal at -2, the main diagonal, and a super-diagonal at 2).

6	11
7	12
8	13
9	14
10	15
	7 8 9

The first and third columns of matrix B are used to create the sub- and super-diagonals of A respectively. In all three cases though, these two outer columns of B are longer than the resulting diagonals of A. Because of this, only a part of the columns is used in A.

When m == n or m > n, spdiags takes elements of the super-diagonal in A from the lower part of the corresponding column of B, and elements of the sub-diagonal in A from the upper part of the corresponding column of B.

When m < n, spdiags does the opposite, taking elements of the super-diagonal in A from the upper part of the corresponding column of B, and elements of the sub-diagonal in A from the lower part of the corresponding column of B.

Part 1 – m is equal to n.

 $A = full(spdiags(B, [-2 \ 0 \ 2], 5, 5))$ Matrix B Matrix A 13 == spdiags =>

A(3,1), A(4,2), and A(5,3) are taken from the upper part of B(:,1).

A(1,3), A(2,4), and A(3,5) are taken from the lower part of B(:,3).

Part 2 – m is greater than n.

 $A = full(spdiags(B, [-2 \ 0 \ 2], 5, 4))$ Matrix B Matrix A 13 == spdiags =>

Same as in Part A.

Part 3 – m is less than n.

```
A = full(spdiags(B, [-2 \ 0 \ 2], 4, 5))
 Matrix B
                                 Matrix A
1
     6
         11
                              6
                                   0
                                       11
                                              0
                                                   0
2
     7
         12
                              0
                                   7
                                        0
                                             12
                                                   0
3
     8
         13 == spdiags =>
                            3
                                   0
                                        8
                                              0
                                                  13
     9
                              0
                                   4
                                        0
                                              9
                                                   0
4
         14
5
    10
         15
```

A(3,1) and A(4,2) are taken from the lower part of B(:,1).

 $A(1,3), A(2,4), \, \text{and} \, A(3,5)$ are taken from the upper part of B(:,3).

Example 5B

Extract the diagonals from the first part of this example back into a column format using the command

B = spdiags(A)

You can see that in each case the original columns are restored (minus those elements that had overflowed the super- and sub-diagonals of matrix A).

Part 1.

Matrix A						Ма	trix	В
6	0	13	0	0		1	6	0
0	7	0	14	0		2	7	0
1	0	8	0	15	== spdiags =>	3	8	13
0	2	0	9	0		0	9	14
0	0	3	0	10		0	10	15

Part 2.

Matrix A Matrix B

6	0	13	0		1	6	0
0	7	0	14		2	7	0
1	0	8	0	== spdiags =>	3	8	13
0	2	0	9		0	9	14
0	0	3	0				

Part 3.

Matrix A							Mat	rix	В
6	; (0.	11	0	0		0	6	11
0) .	7	0	12	0		0	7	12
3	; (0	8	0	13	== spdiags =>	3	8	13
0) .	4	0	9	0		4	9	0

See Also

diag, speye

specular

Purpose	Calculate specular reflectance
Syntax	R = specular(Nx,Ny,Nz,S,V)
Description	R = specular(Nx,Ny,Nz,S,V) returns the reflectance of a surface with normal vector components [Nx,Ny,Nz]. S and V specify the direction to the light source and to the viewer, respectively. You can specify these directions as three vectors[x,y,z] or two vectors [Theta Phi (in spherical coordinates).
	The specular highlight is strongest when the normal vector is in the direction of $(S+V)/2$ where S is the source direction, and V is the view direction.
	The surface spread exponent can be specified by including a sixth argument as in specular(Nx,Ny,Nz,S,V,spread).

Purpose	Sparse identity matrix
Syntax	S = speye(m,n) S = speye(n)
Description	S = speye(m,n) forms an m-by-n sparse matrix with 1s on the main diagonal.
	S = speye(n) abbreviates speye(n,n).
Examples	<pre>I = speye(1000) forms the sparse representation of the 1000-by-1000 identity matrix, which requires only about 16 kilobytes of storage. This is the same final result as I = sparse(eye(1000,1000)), but the latter requires eight megabytes for temporary storage for the full representation.</pre>
See Also	spalloc, spones, spdiags, sprand, sprandn

spfun

Purpose	Apply function to nonzero sparse matrix elements			
Syntax	f = spfun(fun,S)			
Description	The spfun function selectively applies a function to only the <i>nonzero</i> elements of a sparse matrix S, preserving the sparsity pattern of the original matrix (except for underflow or if fun returns zero for some nonzero elements of S).			
	f = spfun(fun,S) evaluates fun(S) on the nonzero elements of S.fun is a function handle. See "Function Handles" in the MATLABProgramming documentation for more information.			
	"Parameterizing Functions" in the MATLAB Mathematics documentation, explains how to provide additional parameters to the function fun, if necessary.			
Remarks	Functions that operate element-by-element, like those in the elfun directory, are the most appropriate functions to use with spfun.			
Examples	Given the 4-by-4 sparse diagonal matrix			
	S = spdiags([1:4]',0,4,4)			
	S = (1,1) 1 (2,2) 2 (3,3) 3 (4,4) 4			
	Because fun returns nonzero values for all nonzero element of S, f = $spfun(@exp,S)$ has the same sparsity pattern as S.			
	f = (1,1) 2.7183 (2,2) 7.3891 (3,3) 20.0855 (4,4) 54.5982			

whereas exp(S) has 1s where S has 0s. full(exp(S)) ans = 1.0000 2.7183 1.0000 1.0000 1.0000 7.3891 1.0000 1.0000 20.0855 1.0000 1.0000 1.0000 1.0000 1.0000 1.0000 54.5982

See Also function_handle (@)


2 - 3577

sph2cart

Purpose	Transform spherical coordinates to Cartesian	
Syntax	<pre>[x,y,z] = sph2cart(THETA,PHI,R)</pre>	
Description	[x,y,z] = sph2cart(THETA,PHI,R) transforms the corresponding elements of spherical coordinate arrays to Cartesian, or <i>xyz</i> , coordinates. THETA, PHI, and R must all be the same size (or any of them can be scalar). THETA and PHI are angular displacements in radians from the positive <i>x</i> -axis and from the <i>x-y</i> plane, respectively.	

Algorithm

The mapping from spherical coordinates to three-dimensional Cartesian coordinates is




```
x = r .* cos(phi) .* cos(theta)
y = r .* cos(phi) .* sin(theta)
z = r .* sin(phi)
```

See Also

cart2pol, cart2sph, pol2cart


Purpose	Generate sphere		
Syntax	sphere sphere(n) [X,Y,Z] = sphere(n)		
Description	The sphere function generates the x -, y -, and z -coordinates of a unit sphere for use with surf and mesh.		
	sphere generates a sphere consisting of 20-by-20 faces.		
	sphere(n) draws a surf plot of an n-by-n sphere in the current figure.		
	[X,Y,Z] = sphere(n) returns the coordinates of a sphere in three matrices that are $(n+1)$ -by- $(n+1)$ in size. You draw the sphere with $surf(X,Y,Z)$ or $mesh(X,Y,Z)$.		
Examples	Generate and plot a sphere.		
	sphere axis equal		

sphere



Plot multiple spheres, translating centers away from the origin:

```
 [x,y,z] = sphere; \\ surf(x,y,z) & sphere centered at origin \\ hold on \\ surf(x+3,y-2,z) & sphere centered at (3,-2,0) \\ surf(x,y+1,z-3) & sphere centered at (0,1,-3) \\ daspect([1 1 1]) \\ \end{cases}
```



See Also cylinder, axis equal

"Polygons and Surfaces" on page 1-100 for related functions

spinmap

Purpose	Spin colormap
Syntax	<pre>spinmap spinmap(t) spinmap(t,inc) spinmap('inf')</pre>
Description	The spinmap function shifts the colormap RGB values by some incremental value. For example, if the increment equals 1, color 1 becomes color 2, color 2 becomes color 3, etc.
	spinmap cyclically rotates the colormap for approximately five seconds using an incremental value of 2.
	<pre>spinmap(t) rotates the colormap for approximately 10*t seconds. The amount of time specified by t depends on your hardware configuration (e.g., if you are running MATLAB software over a network).</pre>
	spinmap(t,inc) rotates the colormap for approximately $10*t$ seconds and specifies an increment inc by which the colormap shifts. When inc is 1, the rotation appears smoother than the default (i.e., 2). Increments greater than 2 are less smooth than the default. A negative increment (e.g., -2) rotates the colormap in a negative direction.
	<pre>spinmap('inf') rotates the colormap for an infinite amount of time. To break the loop, press Ctrl+C.</pre>
See Also	colormap, colormapeditor "Color Operations" on page 1-108 for related functions

Purpose	Cubic spline data interpolation

```
Syntax yy = spline(x,Y,xx)
pp = spline(x,Y)
```

Description yy = spline(x, Y, xx) uses a cubic spline interpolation to find yy, the values of the underlying function Y at the values of the interpolant xx. For the interpolation, the independent variable is assumed to be the final dimension of Y with the breakpoints defined by x.

The sizes of xx and yy are related as follows:

- If Y is a scalar or vector, yy has the same size as xx.
- If Y is an array that is not a vector,
 - If xx is a scalar or vector, size(yy) equals [d1, d2, ..., dk, length(xx)].
 - If xx is an array of size [m1,m2,...,mj], size(yy) equals [d1,d2,...,dk,m1,m2,...,mj].

pp = spline(x,Y) returns the piecewise polynomial form of the cubic spline interpolant for later use with ppval and the spline utility unmkpp. x must be a vector. Y can be a scalar, a vector, or an array of any dimension, subject to the following conditions:

- If x and Y are vectors of the same size, the not-a-knot end conditions are used.
- If x or Y is a scalar, it is expanded to have the same length as the other and the not-a-knot end conditions are used. (See Exceptions (1) below).
- If Y is a vector that contains two more values than x has entries, the first and last value in Y are used as the endslopes for the cubic spline. (See Exceptions (2) below.)

Exceptions

- If Y is a vector that contains two more values than x has entries, the first and last value in Y are used as the endslopes for the cubic spline. If Y is a vector, this means
 - f(x) = Y(2:end-1)
 - df(min(x)) = Y(1)
 - df(max(x)) = Y(end)
- 2 If Y is a matrix or an N-dimensional array with size(Y,N) equal to length(x)+2, the following hold:
 - f(x(j)) matches the value Y(:,...,:,j+1) for j=1:length(x)
 - Df(min(x)) matches Y(:,:,...:,1)
 - Df(max(x)) matches Y(:,:,...:,end)


Note You can also perform spline interpolation using the interp1 function with the command interp1(x,y,xx, 'spline'). Note that while spline performs interpolation on rows of an input matrix, interp1 performs interpolation on columns of an input matrix.

Examples

Example 1

This generates a sine curve, then samples the spline over a finer mesh.

x = 0:10; y = sin(x); xx = 0:.25:10; yy = spline(x,y,xx); plot(x,y,'o',xx,yy)




Example 2

This illustrates the use of clamped or complete spline interpolation where end slopes are prescribed. Zero slopes at the ends of an interpolant to the values of a certain distribution are enforced.

```
x = -4:4;
y = [0 .15 1.12 2.36 2.36 1.46 .49 .06 0];
cs = spline(x,[0 y 0]);
xx = linspace(-4,4,101);
plot(x,y,'o',xx,ppval(cs,xx),'-');
```

spline



Example 3

The two vectors

t	=	1900:10:1	1990;				
р	=	[75.995	91.972	105.711	123.203	131.669	
		150.697	179.323	203.212	226.505	249.633];

represent the census years from 1900 to 1990 and the corresponding United States population in millions of people. The expression

spline(t,p,2000)

uses the cubic spline to extrapolate and predict the population in the year 2000. The result is


ans = 270.6060

Example 4

The statements

```
x = pi*[0:.5:2];
y = [0 1 0 -1 0 1 0;
    1 0 1 0 -1 0 1];
pp = spline(x,y);
yy = ppval(pp, linspace(0,2*pi,101));
plot(yy(1,:),yy(2,:),'-b',y(1,2:5),y(2,2:5),'or'), axis equal
```


generate the plot of a circle, with the five data points $y(:,2), \ldots, y(:,6)$ marked with o's. Note that this y contains two more values (i.e., two more columns) than does x, hence y(:,1) and y(:,end) are used as endslopes.



Example 5

The following code generates sine and cosine curves, then samples the splines over a finer mesh.

```
x = 0:.25:1;
Y = [sin(x); cos(x)];
xx = 0:.1:1;
YY = spline(x,Y,xx);
plot(x,Y(1,:),'o',xx,YY(1,:),'-'); hold on;
plot(x,Y(2,:),'o',xx,YY(2,:),':'); hold off;
```



Algorithm

A tridiagonal linear system (with, possibly, several right sides) is being solved for the information needed to describe the coefficients of the various cubic polynomials which make up the interpolating spline. spline uses the functions ppval, mkpp, and unmkpp. These routines form a small suite of functions for working with piecewise polynomials. For access to more advanced features, see the M-file help for these functions and the Spline Toolbox.

See Also interp1, ppval, mkpp, pchip, unmkpp

References [1] de Boor, C., *A Practical Guide to Splines*, Springer-Verlag, 1978.

spones

Purpose	Replace nonzero sparse matrix elements with ones
Syntax	R = spones(S)
Description	R = spones(S) generates a matrix R with the same sparsity structure as S, but with 1's in the nonzero positions.
Examples	<pre>c = sum(spones(S)) is the number of nonzeros in each column.</pre> r = sum(spones(S'))' is the number of nonzeros in each row. sum(c) and sum(r) are equal, and are equal to nnz(S).
See Also	nnz, spalloc, spfun

Purpose	Set parameters for sparse matrix routines		
Syntax	<pre>spparms('key',value) spparms values = spparms [keys,values] = spparms spparms(values) value = spparms('key') spparms('default') spparms('tight')</pre>		
Description	<pre>spparms('key',value) sets one or more of the tunable parameters used in the sparse routines. In ordinary use, you should never need to deal with this function.</pre>		
	The meanings of the key parameters are		
	'spumoni' Sparse Monitor flag:		
	0	Produces no diagnostic output, the default	
	1	Produces information about choice of algorithm based on matrix structure, and about storage allocation	
	2	Also produces very detailed information about the sparse matrix algorithms	
	'thr_rel', 'thr_abs'	Minimum degree threshold is thr_rel*mindegree + thr_abs.	
	'exact_d'	Nonzero to use exact degrees in minimum degree. Zero to use approximate degrees.	
	'supernd'	If positive, minimum degree amalgamates the supernodes every supernd stages.	
	'rreduce'	If positive, minimum degree does row reduction	

every rreduce stages.

'wh_frac'	Rows with density > wh_frac are ignored in colmmd.
'autommd'	Nonzero to use minimum degree (MMD) orderings with QR-based \smallsetminus and /.
'autoamd'	Nonzero to use colamd ordering with the UMFPACK LU-based $\$ and /, and to use amd with CHOLMOD Cholesky-based $\$ and /.
'piv_tol'	Pivot tolerance used by the UMFPACK LU-based \smallsetminus and /.
'bandden'	Band density used by LAPACK-based $\$ and / for banded matrices. Band density is defined as (# nonzeros in the band)/(# nonzeros in a full band). If bandden = 1.0, never use band solver. If bandden = 0.0, always use band solver. Default is 0.5.
'umfpack'	Nonzero to use UMFPACK instead of the v4 LU-based solver in $\$ and /.
'sym_tol'	Symmetric pivot tolerance used by UMFPACK. See 1u for more information about the role of the symmetric pivot tolerance.

Note LU-based $\ \ and / (UMFPACK)$ on square matrices use a modified colamd or amd. Cholesky-based $\ \ and / (CHOLMOD)$ on symmetric positive definite matrices use amd. QR-based $\ \ and /$ on rectangular matrices use colmmd.

spparms, by itself, prints a description of the current settings.

values = spparms returns a vector whose components give the current settings.

[keys,values] = spparms returns that vector, and also returns a character matrix whose rows are the keywords for the parameters.

spparms(values), with no output argument, sets all the parameters to the values specified by the argument vector.

value = spparms('key') returns the current setting of one parameter.

spparms('default') sets all the parameters to their default settings.

spparms('tight') sets the minimum degree ordering parameters to their *tight* settings, which can lead to orderings with less fill-in, but which make the ordering functions themselves use more execution time.

	Keyword	Default	Tight
values(1)	'spumoni'	0.0	
values(2)	'thr_rel'	1.1	1.0
values(3)	'thr_abs'	1.0	0.0
values(4)	'exact_d'	0.0	1.0
values(5)	'supernd'	3.0	1.0
values(6)	'rreduce'	3.0	1.0
values(7)	'wh_frac'	0.5	0.5
values(8)	'autommd'	1.0	
values(9)	'autoamd'	1.0	
values(10)	'piv_tol'	0.1	
values(11)	'bandden'	0.5	
values(12)	'umfpack'	1.0	
values(13)	'sym_tol'	0.001	

The key parameters for default and tight settings are

Notes

Sparse A\b on Symmetric Positive Definite A

Sparse A b on symmetric positive definite A uses CHOLMOD in conjunction with the amd reordering routine.

The parameter 'autoamd' turns the amd reordering on or off within the solver.

Sparse A\b on General Square A

Sparse A\b on general square A usually uses UMFPACK in conjunction with amd or a modified colamd reordering routine.

The parameter 'umfpack' turns the use of the UMFPACK software on or off within the solver.

If UMFPACK is used,

- The parameter 'piv tol' controls pivoting within the solver.
- The parameter 'autoamd' turns amd and the modified colamd on or off within the solver.

If UMFPACK is not used,

- An LU-based solver is used in conjunction with the colmmd reordering routine.
- If UMFPACK is not used, then the parameter 'autommd' turns the colmmd reordering routine on or off within the solver.
- If UMFPACK is not used and colmmd is used within the solver, then the minimum degree parameters affect the reordering routine within the solver.

Sparse A\b on Rectangular A

Sparse A\b on rectangular A uses a QR-based solve in conjunction with the colmmd reordering routine.

The parameter 'autommd' turns the colmmd reordering on or off within the solver.

If colmmd is used within the solver, then the minimum degree parameters affect the reordering routine within the solver.

See Also \, chol, lu, qr, colamdsymamd

References [1] Gilbert, John R., Cleve Moler, and Robert Schreiber, "Sparse Matrices in MATLAB: Design and Implementation," *SIAM Journal on Matrix Analysis and Applications*, Vol. 13, 1992, pp. 333-356.

[2] Davis, T. A., UMFPACK Version 4.6 User Guide (http://www.cise.ufl.edu/research/sparse/umfpack/), Dept. of Computer and Information Science and Engineering, Univ. of Florida, Gainesville, FL, 2002.

[3] Davis, T. A., CHOLMOD Version 1.0 User Guide (http://www.cise.ufl.edu/research/sparse/cholmod), Dept. of Computer and Information Science and Engineering, Univ. of Florida, Gainesville, FL, 2005.

sprand

Purpose	Sparse uniformly distributed random matrix
Syntax	<pre>R = sprand(S) R = sprand(m,n,density) R = sprand(m,n,density,rc)</pre>
Description	R = sprand(S) has the same sparsity structure as S, but uniformly distributed random entries.
	R = sprand(m,n,density) is a random, m-by-n, sparse matrix with approximately density*m*n uniformly distributed nonzero entries (0 <= density <= 1).
	R = sprand(m,n,density,rc) also has reciprocal condition number approximately equal to rc. R is constructed from a sum of matrices of rank one.
	If rc is a vector of length lr , where $lr \leq min(m,n)$, then R has rc as its first lr singular values, all others are zero. In this case, R is generated by random plane rotations applied to a diagonal matrix with the given singular values. It has a great deal of topological and algebraic structure.
	\ensuremath{sprand} uses the internal state information set with the \ensuremath{rand} function.
See Also	sprandn, sprandsym

Purpose	Sparse normally distributed random matrix
Syntax	<pre>R = sprandn(S) R = sprandn(m,n,density) R = sprandn(m,n,density,rc)</pre>
Description R = sprandn(S) has the same sparsity structure as S, but no distributed random entries with mean 0 and variance 1.	
	R = sprandn(m,n,density) is a random, m-by-n, sparse matrix with approximately density*m*n normally distributed nonzero entries ((0 <= density <= 1).
	R = sprandn(m,n,density,rc) also has reciprocal condition number approximately equal to rc. R is constructed from a sum of matrices of rank one.
	If rc is a vector of length lr, where $lr \leq min(m,n)$, then R has rc as its first lr singular values, all others are zero. In this case, R is generated by random plane rotations applied to a diagonal matrix with the given singular values. It has a great deal of topological and algebraic structure.
	${\tt sprandn}$ uses the internal state information set with the ${\tt randn}$ function.
See Also	sprand, sprandsym

sprandsym

Purpose	Sparse symmetric random matrix
Syntax	<pre>R = sprandsym(S) R = sprandsym(n,density) R = sprandsym(n,density,rc) R = sprandsym(n,density,rc,kind)</pre>
Description	R = sprandsym(S) returns a symmetric random matrix whose lower triangle and diagonal have the same structure as S. Its elements are normally distributed, with mean 0 and variance 1.
	R = sprandsym(n,density) returns a symmetric random, n-by-n, sparse matrix with approximately density*n*n nonzeros; each entry is the sum of one or more normally distributed random samples, and (0 <= density <= 1).
	R = sprandsym(n,density,rc) returns a matrix with a reciprocal condition number equal to rc. The distribution of entries is nonuniform; it is roughly symmetric about 0; all are in $[-1, 1]$.
	If rc is a vector of length n, then R has eigenvalues rc. Thus, if rc is a positive (nonnegative) vector then R is a positive definite matrix. In either case, R is generated by random Jacobi rotations applied to a diagonal matrix with the given eigenvalues or condition number. It has a great deal of topological and algebraic structure.
	R = sprandsym(n,density,rc,kind) returns a positive definite matrix. Argument kind can be:
	• 1 to generate R by random Jacobi rotation of a positive definite diagonal matrix. R has the desired condition number exactly.
	• 2 to generate an R that is a shifted sum of outer products. R has the desired condition number only approximately, but has less structure.
	• 3 to generate an R that has the same structure as the matrix S and approximate condition number 1/rc. density is ignored.
See Also	sprand, sprandn

sprank


Purpose	Structural rank
Syntax	r = sprank(A)
Description	<pre>r = sprank(A) is the structural rank of the sparse matrix A. For all values of A, sprank(A) >= rank(full(A))</pre>
	In exact arithmetic, sprank(A) == rank(full(sprandn(A))) with a probability of one.
Examples	$A = \begin{bmatrix} 1 & 0 & 2 & 0 \\ 2 & 0 & 4 & 0 \end{bmatrix};$
	A = sparse(A);
	sprank(A)
	ans = 2
	<pre>rank(full(A))</pre>
	ans = 1
See Also	dmperm

sprintf

Format data into string
<pre>str = sprintf(format, A,) [str, errmsg] = sprintf(format, A,)</pre>
<pre>str = sprintf(format, A,) applies the format to all elements of array A and any additional array arguments in column order, and returns the results to string str.</pre>
[<i>str</i> , <i>errmsg</i>] = sprintf(<i>format</i> , <i>A</i> ,) returns an error message string when the operation is unsuccessful. Otherwise, <i>errmsg</i> is empty.
 format String in single quotation marks that describes the format of the output fields. Can include combinations of the following: Percent sign followed by a conversion character, such as '%s' for strings. Operators that describe field width, precision, and other options. Literal text to print. Escape characters, including:
 Single quotation mark Percent character Backslash Alarm Backspace Form feed New line

- \r Carriage return
- \t Horizontal tab
- \v Vertical tab
- \xN Hexadecimal number, N
- N Octal number, *N*

Conversion characters and optional operators appear in the following order (includes spaces for clarity):



The following table lists the available conversion characters and subtypes.

Value Type	Conversion	Details
Integer, signed	%d or %i	Base 10 values
	%ld or %li	64-bit base 10 values
	%hd or %hi	16-bit base 10 values

Value Type	Conversion	Details
Integer,	%u	Base 10
unsigned	%0	Base 8 (octal)
	%X	Base 16 (hexadecimal), lowercase letters a – f
	%X	Same as %x, uppercase letters A–F
	%lu %lo %lx or %lX	64-bit values, base 10, 8, or 16
	%hu %ho %hx or %hX	16-bit values, base 10, 8, or 16
Floating-point number	%f	Fixed-point notation
	%e	Exponential notation, such as 3.141593e+00
	%E	Same as %e, but uppercase, such as 3.141593E+00
	%g	The more compact of %e or %f, with no trailing zeros
	%G	The more compact of %E or %f, with no trailing zeros
	%bx or %bX %bo %bu	Double-precision hexadecimal, octal, or decimal value Example: %bx prints pi as 400921fb54442d18

Value Type	Conversion	Details
	%tx or %tX %to %tu	Single-precision hexadecimal, octal, or decimal value Example: %tx prints pi as 40490fdb
Characters	%C	Single character
	%S	String of characters

Additional operators include:

• Field width

Minimum number of characters to print. Can be a number, or an asterisk (*) to refer to an argument in the input list. For example, the input list ('%12d', intmax) is equivalent to ('%*d', 12, intmax).

• Precision

For %f, %e, or %E:	Number of digits to the right of the decimal point. Example: '%6.4f' prints pi as '3.1416'
For %g or %G	Number of significant digits. Example: '%6.4g' prints pi as ' 3.142'

Can be a number, or an asterisk (*) to refer to an argument in the input list. For example, the input list ('%6.4f', pi) is equivalent to ('%*.*f', 6, 4, pi).

• Flags

Action	Flag	Example
Left-justify.	1 1	%-5.2f
Print sign character (+ or).	'+'	%+5.2f
Insert a space before the value.	-	% 5.2f
Pad with zeros.	'0'	%05.2f
Modify selected numeric conversions:	'#'	%#5.Of
• For %0, %x, or %X, print 0, 0x, or 0X prefix.		
• For %f, %e, or %E, print decimal point even when precision is 0.		
 For %g or %G, do not remove trailing zeros or decimal point. 		

• Identifier

Order for processing inputs. Use the syntax n, where n represents the position of the value in the input list.

```
For example, '%3$s %2$s %1$s %2$s' prints inputs 'A', 'B', 'C' as follows: C B A B.
```

The following limitations apply to conversions:

- Numeric conversions print only the real component of complex numbers.
- If you apply an integer or string conversion to a numeric value that contains a fraction, MATLAB overrides the specified conversion, and uses %e.
- If you apply a string conversion (%s) to integer values, MATLAB:
 - Issues a warning.

- Converts values that correspond to valid character codes to characters. For example, '%s' converts [65 66 67] to ABC.
- Different platforms display exponential notation (such as %e) with a different number of digits in the exponent.

Platform	Example
Windows	1.23e+004
UNIX	1.23e+04

• Different platforms display negative zero (-0) differently.

	Conversion Character		
Platform	%e or %E	% f	%g or %G
Windows	0.000000e+000	0.000000	0
Others	-0.000000e+00	-0.000000	-0

Α

Numeric or character array.

Examples Format floating-point numbers:

sprintf(180 Ef! 1/ons) = 8 4E03E006373

sprintf('%0.5f',1/eps) % 4503599627370496.00000
sprintf('%0.5g',1/eps) % 4.5036e+15

Explicitly convert double-precision values to integers:

```
sprintf('%d',round(pi)) % 3
```

Combine literal text with array values:

sprintf('The array is %dx%d.',2,3) % The array is 2x3

sprintf

On a Windows system, convert PC-style exponential notation (three digits in the exponent) to UNIX style notation (two digits):


```
a = sprintf('%e', 12345.678);
if ispc
    a = strrep(a, 'e+0', 'e+');
end
```

References [1] Kernighan, B. W., and D. M. Ritchie, *The C Programming Language*, Second Edition, Prentice-Hall, Inc., 1988.

[2] ANSI specification X3.159-1989: "Programming Language C," ANSI, 1430 Broadway, New York, NY 10018.

- See Also char | fprintf | int2str | num2str | sscanf
- How To "Formatting Strings"

Purpose	Visualize sparsity pattern
Syntax	spy(S) spy(S,markersize) spy(S,'LineSpec') spy(S,'LineSpec',markersize)
Description	plots the
	spy(S) sparsity pattern of any matrix S.
	<pre>spy(S,markersize), where markersize is an integer, plots the sparsity pattern using markers of the specified point size.</pre>
	<pre>spy(S, 'LineSpec'), where LineSpec is a string, uses the specified plot marker type and color.</pre>
	<pre>spy(S, 'LineSpec', markersize) uses the specified type, color, and size for the plot markers.</pre>
	S is usually a sparse matrix, but full matrices are acceptable, in which case the locations of the nonzero elements are plotted.
	Note spy replaces format +, which takes much more space to display essentially the same information.
Examples	This example plots the 60-by-60 sparse adjacency matrix of the connectivity graph of the Buckminster Fuller geodesic dome. This matrix also represents the soccer ball and the carbon-60 molecule. B = bucky; spy(B)





find, gplot, LineSpec, symamd, symrcm

Purpose	Square root
Syntax	B = sqrt(X)
Description	B = sqrt(X) returns the square root of each element of the array X. For the elements of X that are negative or complex, $sqrt(X)$ produces complex results.
Remarks	See sqrtm for the matrix square root.
Examples	<pre>sqrt((-2:2)') ans =</pre>
See Also	sqrtm, realsqrt

sqrtm

Purpose	Matrix square root
Syntax	X = sqrtm(A) [X, resnorm] = sqrtm(A) [X, alpha, condest] = sqrtm(A)
Description	X = sqrtm(A) is the principal square root of the matrix A, i.e. $X*X = A$.
	X is the unique square root for which every eigenvalue has nonnegative real part. If A has any eigenvalues with negative real parts then a complex result is produced. If A is singular then A may not have a square root. A warning is printed if exact singularity is detected.
	[X, resnorm] = sqrtm(A) does not print any warning, and returns the residual, norm(A-X^2, 'fro')/norm(A, 'fro').
	[X, alpha, condest] = $sqrtm(A)$ returns a stability factor alpha and an estimate condest of the matrix square root condition number of X. The residual norm(A-X^2, 'fro')/norm(A, 'fro') is bounded approximately by n*alpha*eps and the Frobenius norm relative error in X is bounded approximately by n*alpha*condest*eps, where n = max(size(A)).
Remarks	If X is real, symmetric and positive definite, or complex, Hermitian and positive definite, then so is the computed matrix square root.
	Some matrices, like $X = [0 \ 1; \ 0 \ 0]$, do not have any square roots, real or complex, and sqrtm cannot be expected to produce one.
Examples	Example 1
	A matrix representation of the fourth difference operator is
	X =
	5 -4 1 0 0 -4 6 -4 1 0
	-4 6 -4 1 0 1 -4 6 -4 1
	0 1 -4 6 -4

This matrix is symmetric and positive definite. Its unique positive definite square root, Y = sqrtm(X), is a representation of the second difference operator.

Y =				
2	- 1	- 0	- 0	- 0
- 1	2	- 1	0	- 0
0	- 1	2	- 1	0
- 0	0	- 1	2	- 1
- 0	- 0	- 0	- 1	2

Example 2

The matrix

X = 7 10 15 22

has four square roots. Two of them are

Y1 = 1.5667 1.7408 2.6112 4.1779

and

Y2 = 1 2 3 4

The other two are -Y1 and -Y2. All four can be obtained from the eigenvalues and vectors of X.

[V,D] = eig(X); D = 0.1386 0 0 28.8614 The four square roots of the diagonal matrix D result from the four choices of sign in

S = -0.3723 0 0 -5.3723

All four Ys are of the form

Y = V*S/V

The sqrtm function chooses the two plus signs and produces Y1, even though Y2 is more natural because its entries are integers.

See Also expm, funm, logm

Purpose	Remove singleton dimensions
Syntax	B = squeeze(A)
• • • • • • • • • • • • • • • • • • • •	
Description	B = squeeze(A) returns an array B with the same elements as A, but with all singleton dimensions removed. A singleton dimension is any dimension for which size(A,dim) = 1. Two-dimensional arrays are unaffected by squeeze; if A is a row or column vector or a scalar (1-by-1) value, then $B = A$.
Examples	Consider the 2-by-1-by-3 array $Y = rand(2,1,3)$. This array has a singleton column dimension — that is, there's only one column per page.
	Y =
	Y(:,:,1) = Y(:,:,2) = 0.5194 0.0346 0.8310 0.0535 Y(:,:,3) = 0.5297 0.6711 The command Z = squeeze(Y) yields a 2-by-3 matrix: Z =
	0.5194 0.0346 0.5297 0.8310 0.0535 0.6711
	Consider the 1-by-1-by-5 array mat=repmat(1,[1,1,5]). This array has only one scalar value per page.
	mat =
	<pre>mat(:,:,1) = mat(:,:,2) =</pre>

1

1

2-3613

```
mat(:,:,3) = mat(:,:,4) =
    1    1
mat(:,:,5) =
    1
```

The command squeeze(mat) yields a 5-by-1 matrix:

```
See Also reshape, shiftdim
```

Purpose Convert state-space filter parameters to transfer function form

Syntax [b,a] = ss2tf(A,B,C,D,iu)

Description ss2tf converts a state-space representation of a given system to an equivalent transfer function representation.

[b,a] = ss2tf(A,B,C,D,iu) returns the transfer function

$$H(s) = \frac{B(s)}{A(s)} = C(sI - A)^{-1}B + D$$

of the system

$$\dot{x} = Ax + Bu$$

 $y = Cx + Du$

from the iu-th input. Vector a contains the coefficients of the denominator in descending powers of s. The numerator coefficients are returned in array b with as many rows as there are outputs y. ss2tf also works with systems in discrete time, in which case it returns the *z*-transform representation.

The ss2tf function is part of the standard MATLAB language.

Algorithm The ss2tf function uses poly to find the characteristic polynomial det(*sI-A*) and the equality:

$$H(s) = C(sI - A)^{-1}B = \frac{\det(sI - A + BC) - \det(sI - A)}{\det(sI - A)}$$

sscanf

Purpose	Read formatted data from string
Syntax	<pre>A = sscanf(str, format) A = sscanf(str, format, sizeA) [A, count] = sscanf() [A, count, errmsg] = sscanf() [A, count, errmsg, nextindex] = sscanf()</pre>
Description	<pre>A = sscanf(str, format) reads data from string str, converts it according to the format, and returns the results in array A. The sscanf function reapplies the format until either reaching the end of str or failing to match the format. If sscanf cannot match the format to the data, it reads only the portion that matches into A and stops processing. If str is a character array with more than one row, sscanf reads the characters in column order.</pre>
	A = sscanf(str, format, sizeA) reads sizeA elements into A, where sizeA can be an integer or can have the form $[m,n]$.
	<pre>[A, count] = sscanf() returns the number of elements that sscanf successfully reads.</pre>
	<pre>[A, count, errmsg] = sscanf() returns an error message string when the operation is unsuccessful. Otherwise, errmsg is an empty string.</pre>
	[A, count, errmsg, nextindex] = sscanf() returns one more than the number of characters scanned in str.
Input	format
Arguments	String enclosed in single quotation marks that describes each type of element (field). Includes one or more of the following specifiers.

Field Type	Specifier	Details
	-	
Integer, signed	%d	Base 10
	%i	Base determined from the values. Defaults to base 10. If initial digits are 0x or 0X, it is base 16. If initial digit is 0, it is base 8.
Integer,	%u	Base 10
unsigned	[%] 0	Base 8 (octal)
	%X	Base 16 (hexadecimal)
Floating-point	%f	Floating-point fields can contain any of the following (not case sensitive): Inf, -Inf, NaN, or -NaN.
number	%e	
	%g	
Character string	[∞] S	Read series of characters, until find white space.
	%C	Read any single character, including white space. (To read multiple characters, specify field length.)
	%[]	Read only characters in the brackets, until the first nonmatching character or white space.

Optionally:

- To skip fields, insert an asterisk (*) after the percent sign (%). For example, to skip integers, specify %*d.
- To specify the maximum width of a field, insert a number. For example, %10c reads exactly 10 characters at a time, including white space.

	in the numb sizeA	p a specific set of characters, insert the literal characters <i>format</i> . For example, to read only the floating-point er from 'pi=3.14159', specify a <i>format</i> of 'pi=%f'.
	inf	Read to the end of the input string. (default)
	n	Read at most <i>n</i> elements.
	[<i>m</i> , <i>n</i>]	Read at most <i>m</i> * <i>n</i> elements in column order. <i>n</i> can be inf, but <i>m</i> cannot.
		e <i>format</i> includes % s , <i>A</i> can contain more than <i>n</i> columns. to elements, not characters.
	str	
	Characte	er string.
Output Arguments	A An array	v. If the <i>format</i> includes:
	is inf	numeric specifiers, A is numeric, of class double. If <i>sizeA</i> or <i>n</i> , then A is a column vector. If the input contains than <i>sizeA</i> elements, MATLAB pads A with zeros.
	array.	character or string specifiers (%c or %s), A is a character If <i>sizeA</i> is <i>inf</i> or <i>n</i> , A is a row vector. If the input ns fewer than <i>sizeA</i> characters, MATLAB pads A with 0).
	nume to its the fo	bination of numeric and character specifiers, A is ric, of class double. MATLAB converts each character numeric equivalent. This conversion occurs even when ormat explicitly skips all numeric values (for example, mat of '%*d %s').

If MATLAB cannot match the input to the *format*, and the *format* contains both numeric and character specifiers, *A* can be numeric or character. The class of *A* depends on the values MATLAB reads before processing stops.

count

Number of elements sscanf reads into A.

errmsg

An error message string when sscanf cannot open the specified file. Otherwise, an empty string.

nextindex

sscanf counts the number of characters **sscanf** reads from *str*, and then adds one.

Examples Example 1

Read multiple floating-point values from a string:

Example 2

Read an octal integer from a string, identified by the '0' prefix, using %i to preserve the sign:

```
sscanf('-010','%i')
ans =
-8
```

Example 3

Read numeric values from a two-dimensional character array. By default, sscanf reads characters in column order. To preserve the original order of the values, read one row at a time.

```
mixed = ['abc 45 6 ghi'; 'def 7 89 jkl'];
[nrows, ncols] = size(mixed);
for k = 1:nrows
    nums(k,:) = sscanf(mixed(k,:), '%*s %d %d %*s', [1, inf]);
end;
% type the variable name to see the result
nums =
    45     6
    7     89
```

Example 4

sscanf finds one match for %s

```
[str count] = sscanf('ThisIsOneString', '%s')
str =
ThisIsOneString
count =
1
```

sscanf finds four matches for %s. Because it does not match space characters, there are no spaces in the output string:

```
[str count] = sscanf('These Are Four Strings', '%s')
str =
TheseAreFourStrings
count =
4
```

sscanf finds five word matches for %s and four space character matches for %c. Because the %c specifier does match a space character, the output string does include spaces:

```
[str count] = sscanf('Five strings and four spaces', '%s%c')
str =
    Five strings and four spaces
count =
    9
```

sscanf finds three word matches for %s and two numeric matches for %d. Because the format specifier has a mixed %d and %s format, sscanf converts all nonnumeric characters to numeric:

```
[str count] = sscanf('5 strings and 4 spaces', '%d%s%s%d%s');
str'
  Columns 1 through 9
     5
         115
               116
                      114
                            105
                                  110
                                         103
                                               115
                                                      97
  Columns 10 through 18
   110
         100
                 4
                     115
                            112
                                   97
                                         99
                                               101
                                                     115
count
count =
     5
```

Example 5


```
[str, count] = sscanf('one two three', '%c')
str =
    one two three
count =
    13
[str, count] = sscanf('one two three', '%13c')
str =
    one two three
count =
    1
```

Example 6

See Also fscanf | sprintf | textscan

Purpose	Stairstep graph
GUI Alternatives	To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.
Syntax	<pre>stairs(Y) stairs(X,Y) stairs(,LineSpec) stairs(,'PropertyName',propertyvalue) stairs(axes_handle,) h = stairs() [xb,yb] = stairs(Y,)</pre>
Description	 Stairstep graphs are useful for drawing time-history graphs of digitally sampled data. stairs(Y) draws a stairstep graph of the elements of Y, drawing one line per column for matrices. The axes ColorOrder property determines the color of the lines. When Y is a vector, the x-axis scale ranges from 1 to length(Y). When Y is a matrix, the x-axis scale ranges from 1 to the number of rows in Y. stairs(X,Y) plots the elements in Y at the locations specified in X. X must be the same size as Y or, if Y is a matrix, X can be a row or a column vector such that
	<pre>length(X) = size(Y,1)</pre>

	<pre>stairs(,LineSpec) specifies a line style, marker symbol, and color for the graph. (See LineSpec for more information.)</pre>
	<pre>stairs(,'PropertyName',propertyvalue) creates the stairstep graph, applying the specified property settings. See Stairseries properties for a description of properties.</pre>
	<pre>stairs(axes_handle,) plots into the axes with the handle axes_handle instead of into the current axes object (gca).</pre>
	h = stairs() returns the handles of the stairseries objects created (one per matrix column).
	<pre>[xb,yb] = stairs(Y,) does not draw graphs, but returns vectors xb and yb such that plot(xb,yb) plots the stairstep graph.</pre>
Examples	Create a stairstep plot of a sine wave.
	<pre>x = linspace(-2*pi,2*pi,40); stairs(x,sin(x))</pre>



See Alsobar, hist, stem"Discrete Data Plots" on page 1-99 for related functionsStairseries Properties for property descriptions

Stairseries Properties

Purpose	Define stairseries properties
Modifying Properties	You can set and query graphics object properties using the set and get commands or the Property Editor (propertyeditor).
	Note that you cannot define default property values for stairseries objects.
	See Plot Objects for information on stairseries objects.
Stairseries Property	This section provides a description of properties. Curly braces {} enclose default values.
Descriptions	Annotation hg.Annotation object Read Only
	Control the display of stairseries objects in legends. The Annotation property enables you to specify whether this stairseries object is represented in a figure legend.
	Querying the Annotation property returns the handle of an hg.Annotation object. The hg.Annotation object has a property called LegendInformation, which contains an hg.LegendEntry object.
	Once you have obtained the hg.LegendEntry object, you can set its IconDisplayStyle property to control whether the stairseries object is displayed in a figure legend:

IconDisplayStyle Value	Purpose
on	Include the stairseries object in a legend as one entry, but not its children objects
off	Do not include the stairseries or its children in a legend (default)
children	Include only the children of the stairseries as separate entries in the legend

Setting the IconDisplayStyle Property

These commands set the IconDisplayStyle of a graphics object with handle hobj to children, which causes each child object to have an entry in the legend:

```
hAnnotation = get(hobj,'Annotation');
hLegendEntry = get(hAnnotation,'LegendInformation');
set(hLegendEntry,'IconDisplayStyle','children')
```

Using the IconDisplayStyle Property

See "Controlling Legends" for more information and examples.

BeingDeleted

on | {off} Read Only

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions might not need to perform actions on objects if the objects are going to be deleted, and therefore, can check the object's BeingDeleted property before acting.

```
BusyAction
```

cancel | {queue}

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callbacks. If there is a callback function executing, callbacks invoked subsequently always attempt to interrupt it.

If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are

- cancel Discard the event that attempted to execute a second callback routine.
- queue Queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn

string or function handle

Button press callback function. A callback that executes whenever you press a mouse button while the pointer is over this object, but not over another graphics object. See the HitTestArea property for information about selecting objects of this type.

See the figure's SelectionType property to determine if modifier keys were also pressed.

This property can be

• A string that is a valid MATLAB expression

- The name of a MATLAB file
- A function handle

Set this property to a function handle that references the callback. The expressions execute in the MATLAB workspace.

See "Function Handle Callbacks" for information on how to use function handles to define the callbacks.

The expression executes in the MATLAB workspace.

See Function Handle Callbacks for information on how to use function handles to define the callbacks.

Children

array of graphics object handles

Children of the stairseries object. An array containing the handles of all line objects parented to the stairseries object (whether visible or not).

If a child object's HandleVisibility property is callback or off, its handle does not show up in this object's Children property. If you want the handle in the Children property, set the root ShowHiddenHandles property to on. For example:

set(0, 'ShowHiddenHandles', 'on')

Clipping

{on} | off

Clipping mode. MATLAB clips graphs to the axes plot box by default. If you set Clipping to off, portions of graphs can be displayed outside the axes plot box. This can occur if you create a plot object, set hold to on, freeze axis scaling (axis manual), and then create a larger plot object.

Color

ColorSpec

Color of the object. A three-element RGB vector or one of the MATLAB predefined names, specifying the object's color.

See the ColorSpec reference page for more information on specifying color.

CreateFcn

string or function handle

Callback routine executed during object creation. This property defines a callback that executes when MATLAB creates an object. You must specify the callback during the creation of the object. For example,

graphicfcn(y, 'CreateFcn',@CallbackFcn)

where @CallbackFcn is a function handle that references the callback function and graphicfcn is the plotting function which creates this object.

MATLAB executes this routine after setting all other object properties. Setting this property on an existing object has no effect.

The handle of the object whose CreateFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DeleteFcn

string or function handle

Callback executed during object deletion. A callback that executes when this object is deleted (e.g., this might happen when you issue a delete command on the object, its parent axes, or the figure containing it). MATLAB executes the callback before destroying the object's properties so the callback routine can query these values.

The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which can be queried using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

See the BeingDeleted property for related information.

DisplayName

string (default is empty string)

String used by legend for this stairseries object. The legend function uses the string defined by the DisplayName property to label this stairseries object in the legend.

- If you specify string arguments with the legend function, DisplayName is set to this stairseries object's corresponding string and that string is used for the legend.
- If DisplayName is empty, legend creates a string of the form, ['data' n], where n is the number assigned to the object based on its location in the list of legend entries. However, legend does not set DisplayName to this string.
- If you edit the string directly in an existing legend, DisplayName is set to the edited string.
- If you specify a string for the DisplayName property and create the legend using the figure toolbar, then MATLAB uses the string defined by DisplayName.

• To add programmatically a legend that uses the DisplayName string, call legend with the toggle or show option.

See "Controlling Legends" for more examples.

EraseMode

{normal} | none | xor | background

Erase mode. This property controls the technique MATLAB uses to draw and erase objects and their children. Alternative erase modes are useful for creating animated sequences, where control of the way individual objects are redrawn is necessary to improve performance and obtain the desired effect.

- normal Redraw the affected region of the display, performing the three-dimensional analysis necessary to ensure that all objects are rendered correctly. This mode produces the most accurate picture, but is the slowest. The other modes are faster, but do not perform a complete redraw and are therefore less accurate.
- none Do not erase objects when they are moved or destroyed. While the objects are still visible on the screen after erasing with EraseMode none, you cannot print these objects because MATLAB stores no information about their former locations.
- xor Draw and erase the object by performing an exclusive OR (XOR) with each pixel index of the screen behind it. Erasing the object does not damage the color of the objects behind it. However, the color of the erased object depends on the color of the screen behind it and it is correctly colored only when it is over the axes background color (or the figure background color if the axes Color property is set to none). That is, it isn't erased correctly if there are objects behind it.
- background Erase the graphics objects by redrawing them in the axes background color, (or the figure background color if the axes Color property is set to none). This damages other

graphics objects that are behind the erased object, but the erased object is always properly colored.

Printing with Nonnormal Erase Modes

MATLAB always prints figures as if the EraseMode of all objects is normal. This means graphics objects created with EraseMode set to none, xor, or background can look different on screen than on paper. On screen, MATLAB can mathematically combine layers of colors (e.g., performing an XOR on a pixel color with that of the pixel behind it) and ignore three-dimensional sorting to obtain greater rendering speed. However, these techniques are not applied to the printed output.

Set the axes background color with the axes Color property. Set the figure background color with the figure Color property.

You can use the MATLAB getframe command or other screen capture applications to create an image of a figure containing nonnormal mode objects.

HandleVisibility

{on} | callback | off

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally accessing objects that you need to protect for some reason.

- on Handles are always visible when HandleVisibility is on.
- callback Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have access to object handles.

• off — Setting HandleVisibility to off makes handles invisible at all times. This might be necessary when a callback invokes a function that might potentially damage the GUI (such as evaluating a user-typed string) and so temporarily hides its own handles during the execution of that function.

Functions Affected by Handle Visibility

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close.

Properties Affected by Handle Visibility

When a handle's visibility is restricted using callback or off, the object's handle does not appear in its parent's Children property, figures do not appear in the root's CurrentFigure property, objects do not appear in the root's CallbackObject property or in the figure's CurrentObject property, and axes do not appear in their parent's CurrentAxes property.

Overriding Handle Visibility

You can set the root ShowHiddenHandles property to on to make all handles visible regardless of their HandleVisibility settings (this does not affect the values of the HandleVisibility properties). See also findall.

Handle Validity

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties and pass it to any function that operates on handles.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

HitTest

{on} | off

Selectable by mouse click. HitTest determines whether this object can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click on the objects that compose the area graph. If HitTest is off, clicking this object selects the object below it (which is usually the axes containing it).

HitTestArea

on | {off}

Select the object by clicking lines or area of extent. This property enables you to select plot objects in two ways:

- Select by clicking lines or markers (default).
- Select by clicking anywhere in the extent of the plot.

When HitTestArea is off, you must click the object's lines or markers (excluding the baseline, if any) to select the object. When HitTestArea is on, you can select this object by clicking anywhere within the extent of the plot (i.e., anywhere within a rectangle that encloses it).

Interruptible

{on} | off

Callback routine interruption mode. The Interruptible property controls whether an object's callback can be interrupted by callbacks invoked subsequently.

Only callbacks defined for the ButtonDownFcn property are affected by the Interruptible property. MATLAB checks for events that can interrupt a callback only when it encounters a drawnow, figure, getframe, or pause command in the routine. See the BusyAction property for related information.

Setting Interruptible to on allows any graphics object's callback to interrupt callback routines originating from a bar property. Note that MATLAB does not save the state of variables or the display (e.g., the handle returned by the gca or gcf command) when an interruption occurs.

LineStyle

{-} | -- | : | -. | none

Line style. This property specifies the line style of the object. Available line styles are shown in the following table.

Specifier String	Line Style
-	Solid line (default)
	Dashed line
:	Dotted line
	Dash-dot line
none	No line

You can use LineStyle none when you want to place a marker at each point but do not want the points connected with a line (see the Marker property).

LineWidth

scalar

The width of linear objects and edges of filled areas. Specify this value in points (1 point = $1/_{72}$ inch). The default LineWidth is 0.5 points.

Marker

character (see table)

Marker symbol. The Marker property specifies the type of markers that are displayed at plot vertices. You can set values for the Marker property independently from the LineStyle property. Supported markers include those shown in the following table.

Marker Specifier	Description
+	Plus sign
0	Circle
*	Asterisk
	Point
х	Cross
S	Square
d	Diamond
^	Upward-pointing triangle
v	Downward-pointing triangle
>	Right-pointing triangle
<	Left-pointing triangle
р	Five-pointed star (pentagram)
h	Six-pointed star (hexagram)
none	No marker (default)

MarkerEdgeColor

ColorSpec | none | {auto}

Marker edge color. The color of the marker or the edge color for filled markers (circle, square, diamond, pentagram, hexagram, and the four triangles). ColorSpec defines the color to use. none specifies no color, which makes nonfilled markers invisible. auto sets MarkerEdgeColor to the same color as the Color property.

MarkerFaceColor

ColorSpec | {none} | auto

Marker face color. The fill color for markers that are closed shapes (circle, square, diamond, pentagram, hexagram, and the four triangles). ColorSpec defines the color to use. none makes the interior of the marker transparent, allowing the background to show through. auto sets the fill color to the axes color, or to the figure color if the axes Color property is set to none (which is the factory default for axes objects).

MarkerSize

size in points

Marker size. A scalar specifying the size of the marker in points. The default value for MarkerSize is 6 points (1 point = 1/72 inch). Note that MATLAB draws the point marker (specified by the '.' symbol) at one-third the specified size.

Parent

handle of parent axes, hggroup, or hgtransform

Parent of this object. This property contains the handle of the object's parent. The parent is normally the axes, hggroup, or hgtransform object that contains the object.

See "Objects That Can Contain Other Objects" for more information on parenting graphics objects.

```
Selected
```

on | {off}

Is object selected? When you set this property to on, MATLAB displays selection "handles" at the corners and midpoints if the SelectionHighlight property is also on (the default). You can, for example, define the ButtonDownFcn callback to set this property to on, thereby indicating that this particular object is selected. This property is also set to on when an object is manually selected in plot edit mode.

SelectionHighlight

{on} | off

Objects are highlighted when selected. When the Selected property is on, MATLAB indicates the selected state by drawing four edge handles and four corner handles. When SelectionHighlight is off, MATLAB does not draw the handles except when in plot edit mode and objects are selected manually.

Тад

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when you are constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callbacks. You can define Tag as any string.

For example, you might create an areaseries object and set the Tag property.

t = area(Y, 'Tag', 'area1')

When you want to access objects of a given type, you can use findobj to find the object's handle. The following statement changes the FaceColor property of the object whose Tag is area1.

```
set(findobj('Tag','area1'),'FaceColor','red')
```

Туре

string (read only)

Type of graphics object. This property contains a string that identifies the class of the graphics object. For stairseries objects, **Type** is 'hggroup'. The following statement finds all the hggroup objects in the current axes object.

t = findobj(gca, 'Type', 'hggroup');

UIContextMenu

handle of a uicontextmenu object

Associate a context menu with this object. Assign this property the handle of a uicontextmenu object created in the object's parent figure. Use the uicontextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click over the object.

UserData

array

User-specified data. This property can be any data you want to associate with this object (including cell arrays and structures). The object does not set values for this property, but you can access it using the set and get functions.

Visible

{on} | off

Visibility of this object and its children. By default, a new object's visibility is on. This means all children of the object are visible unless the child object's Visible property is set to off. Setting an object's Visible property to off prevents the object from being displayed. However, the object still exists and you can set and query its properties.

XData

array

X-axis location of stairs. The stairs function uses XData to label the x-axis. XData can be either a matrix equal in size to YData or a vector equal in length to the number of rows in YData. That is, length(XData) == size(YData,1).

If you do not specify XData (i.e., the input argument x), the stairs function uses the indices of YData to create the stairstep graph. See the XDataMode property for related information.

XDataMode

{auto} | manual

Use automatic or user-specified x-axis values. If you specify XData (by setting the XData property or specifying the x input argument), MATLAB sets this property to manual and uses the specified values to label the x-axis.

If you set XDataMode to auto after having specified XData, MATLAB resets the *x*-axis ticks to 1:size(YData,1) or to the column indices of the ZData, overwriting any previous values for XData.

XDataSource

string (MATLAB variable)

Link XData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the XData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change XData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

YData

scalar, vector, or matrix

Stairs plot data. YData contains the data plotted in the stairstep graph. Each value in YData is represented by a marker in the stairstep graph. If YData is a matrix, the stairs function creates a line for each column in the matrix.

The input argument y in the stairs function calling syntax assigns values to YData.

YDataSource

string (MATLAB variable)

Link YData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the YData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change YData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

start

Purpose	Start timer(s) running
Syntax	start(obj)
Description	<pre>start(obj) starts the timer running, represented by the timer object, obj. If obj is an array of timer objects, start starts all the timers. Use the timer function to create a timer object.</pre>
	start sets the Running property of the timer object, obj, to 'on', initiates TimerFcn callbacks, and executes the StartFcn callback.
	The timer stops running if one of the following conditions apply:
	• The first TimerFcn callback completes, if ExecutionMode is 'singleShot'.
	• The number of TimerFcn callbacks specified in TasksToExecute have been executed.
	 The stop(obj) command is issued.
	• An error occurred while executing a TimerFcn callback.
See Also	timer, stop

Purpose	Start timer(s) running at specified time
Syntax	<pre>startat(obj,time) startat(obj,S) startat(obj,S,pivotyear) startat(obj,Y,M,D) startat(obj,[Y,M,D]) startat(obj,Y,M,D,H,MI,S) startat(obj,[Y,M,D,H,MI,S])</pre>
Description	<pre>startat(obj,time) starts the timer represented by timer object objrunning at the time specified by the serial date number time. If obj is an array of timer objects, startat starts all the timers running at the specified time. To create a timer object, use the timer function. You can set the starting time to any serial date number less than or equal to 25 days from the current date.</pre>
	startat sets the Running property of the timer object, obj, to 'on', initiates TimerFcn callbacks, and executes the StartFcn callback.
	The serial date number, time, indicates the number of days that have elapsed since 1-Jan-0000 (starting at 1). See datenum for additional information about serial date numbers.
	<pre>startat(obj,S) starts the timer running at the time specified by the date string S. The date string must use date format 0, 1, 2, 6, 13, 14, 15, 16, or 23, as defined by the datestr function. Date strings with two-character years are interpreted to be within the 100 years centered on the current year.</pre>
	startat(obj,S,pivotyear) uses the specified pivot year as the starting year of the 100-year range in which a two-character year resides. The default pivot year is the current year minus 50 years.
	<pre>startat(obj,Y,M,D) startat(obj,[Y,M,D]) start the timer at the year (Y), month (M), and day (D) specified. Y, M, and D must be arrays of the same size (or they can be a scalar).</pre>
	startat(obj,Y,M,D,H,MI,S) startat(obj,[Y,M,D,H,MI,S]) start the timer at the year (Y), month (M), day (D), hour (H), minute (MI), and

	second (S) specified. Y, M, D, H, MI, and S must be arrays of the same size (or they can be a scalar). Values outside the normal range of each array are automatically carried to the next unit (for example, month values greater than 12 are carried to years). Month values less than 1 are set to be 1; all other units can wrap and have valid negative values. The timer stops running if one of the following conditions apply:
	• The number of TimerFcn callbacks specified in TasksToExecute have been executed.
	• The stop(obj) command is issued.
	• An error occurred while executing a TimerFcn callback.
Examples	This example uses a timer object to execute a function at a specified time.
	t1=timer('TimerFcn','disp(''it is 10 o''''clock'')'); startat(t1,'10:00:00');
	This example uses a timer to display a message when an hour has elapsed.
	t2=timer('TimerFcn','disp(''It has been an hour now.'')'); startat(t2,now+1/24);
See Also	datenum, datestr, now, timer, start, stop

Purpose	Startup file for user-defined options
Syntax	startup
Description	startup executes commands of your choosing when the MATLAB program starts.
	Create a startup.m file in your MATLAB startup folder and put in the file any commands you want executed at MATLAB startup. For example, your startup.m file might include physical constants, defaults for Handle Graphics properties, engineering conversion factors, or anything else you want predefined in your workspace.
Algorithm	The MATLAB program executes the matlabrc.m file when it starts. matlabrc.m invokes startup.m, if it exists on the MATLAB search path.
	You can extend this process to create additional startup files, if needed.
	The MathWorks does not recommend modifying the matlabrc.m file, except perhaps by system administrators in network configurations.
See Also	finish, matlabrc, matlabroot, path, quit, userpath
	See "Specifying Startup Options Using the Startup File for the MATLAB Program, startup.m" and Preferences in the MATLAB Desktop Tools and Development Environment documentation.

Syntax s = std(X)
s = std(X,flag)
s = std(X,flag,dim)

Definition There are two common textbook definitions for the standard deviation s of a data vector X.

(1)
$$s = \left(\frac{1}{n-1}\sum_{i=1}^{n} (x_i - \bar{x})^2\right)^{\frac{1}{2}}$$

(2) $s = \left(\frac{1}{n}\sum_{i=1}^{n} (x_i - \bar{x})^2\right)^{\frac{1}{2}}$

where

$$\bar{x} = \frac{1}{n} \sum_{i=1}^{n} x_i$$

and n is the number of elements in the sample. The two forms of the equation differ only in n - 1 versus n in the divisor.

Description

s = std(X), where X is a vector, returns the standard deviation using (1) above. The result s is the square root of an unbiased estimator of the variance of the population from which X is drawn, as long as X consists of independent, identically distributed samples.

If X is a matrix, std(X) returns a row vector containing the standard deviation of the elements of each column of X. If X is a multidimensional array, std(X) is the standard deviation of the elements along the first nonsingleton dimension of X.

	s = std(X, flag) for flag = 0, is the same as $std(X)$. For flag = 1, std(X, 1) returns the standard deviation using (2) above, producing the second moment of the set of values about their mean.
	s = std(X,flag,dim) computes the standard deviations along the dimension of X specified by scalar dim. Set flag to 0 to normalize Y by n -1; set flag to 1 to normalize by n .
Examples	For matrix X $X = \frac{1 & 5 & 9}{7 & 15 & 22}$ $s = std(X,0,1)$ $s = \frac{4.2426}{7.0711} & 9.1924$ $s = std(X,0,2)$ $s = \frac{4.000}{7.5056}$

See Also

corrcoef, cov, mean, median, var

std (timeseries)

Purpose	Standard deviation of timeseries data
Syntax	ts_std = std(ts) ts_std = std(ts,'PropertyName1',PropertyValue1,)
Description	<pre>ts_std = std(ts) returns the standard deviation of the time-series data. When ts.Data is a vector, ts_std is the standard deviation of ts.Data values. When ts.Data is a matrix, ts_std is the standard deviation of each column of ts.Data (when IsTimeFirst is true and the first dimension of ts is aligned with time). For the N-dimensional ts.Data array, std always operates along the first nonsingleton dimension of ts.Data.</pre>
	<pre>ts_std = std(ts, 'PropertyName1', PropertyValue1,) specifies the following optional input arguments:</pre>
	 'MissingData' property has two possible values, 'remove' (default) or 'interpolate', indicating how to treat missing data during the calculation.
	• 'Quality' values are specified by a vector of integers, indicating which quality codes represent missing samples (for vector data) or missing observations (for data arrays with two or more dimensions).
	 'Weighting' property has two possible values, 'none' (default) or 'time'. When you specify 'time', larger time values correspond to larger weights.
Examples	1 Load a 24-by-3 data array.
	load count.dat
	2 Create a timeseries object with 24 time values.
	<pre>count_ts = timeseries(count,1:24,'Name','CountPerSecond')</pre>

3 Calculate the standard deviation of each data column for this timeseries object.

std(count_ts)
ans =
 25.3703 41.4057 68.0281

The standard deviation is calculated independently for each data column in the timeseries object.

See Also iqr (timeseries), mean (timeseries), median (timeseries), var (timeseries), timeseries

stem

Purpose

Plot discrete sequence data




stem(axes_handle,...) plots into the axes object with the handle axes_handle instead of into the current axes object (gca).

h = stem(...) returns a vector of stemseries object handles in h, one handle per column of data in Y.


Examples Single Series of Data

This example creates a stem plot representing the cosine of 10 values linearly spaced between 0 and 2π . Note that the line style of the baseline is set by first getting its handle from the stemseries object's **BaseLine** property.

```
t = linspace(-2*pi,2*pi,10);
h = stem(t,cos(t),'fill','--');
set(get(h,'BaseLine'),'LineStyle',':')
set(h,'MarkerFaceColor','red')
```



The following diagram illustrates the parent-child relationship in the previous stem plot. Note that the stemseries object contains two line objects used to draw the stem lines and the end markers. The baseline is a separate line object.



If you do not want the baseline to show, you can remove it with the following command:

```
delete(get(stem_handle, 'Baseline'))
```

where stem_handle is the handle for the stemseries object. You can use similar code to change the color or style of the baseline, specifying any line property and value, for example,


```
set(get(stem_handle, 'Baseline'), 'LineWidth',3)
```

Two Series of Data on One Graph


The following example creates a stem plot from a two-column matrix. In this case, the **stem** function creates two stemseries objects, one of each column of data. Both objects' handles are returned in the output argument h.

- h(1) is the handle to the stemseries object plotting the expression exp(-.07*x).*cos(x).
- h(2) is the handle to the stemseries object plotting the expression exp(.05*x).*cos(x).

```
x = 0:25;
y = [exp(-.07*x).*cos(x);exp(.05*x).*cos(x)]';
h = stem(x,y);
```



The following diagram illustrates the parent-child relationship in the previous stem plot. Note that each column in the input matrix y results in the creation of a stemseries object, which contains two line objects (one for the stems and one for the markers). The baseline is shared by both stemseries objects.




See Also bar, plot, stairs


Stemseries properties for property descriptions

stem3

Purpose	Plot 3-D discrete sequence data
GUI Alternatives	To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.
Syntax	<pre>stem3(Z) stem3(X,Y,Z) stem3(,'fill') stem3(,LineSpec) h = stem3()</pre>
Description	Three-dimensional stem plots display lines extending from the <i>x-y</i> plane. A circle (the default) or other marker symbol whose <i>z</i> -position represents the data value terminates each stem.
	stem3 (Z) plots the data sequence Z as stems that extend from the x-y plane. x and y are generated automatically. When Z is a row vector, stem3 plots all elements at equally spaced x values against the same y value. When Z is a column vector, stem3 plots all elements at equally spaced y values against the same x value.
	stem3(X,Y,Z) plots the data sequence Z at values specified by X and Y. X, Y, and Z must all be vectors or matrices of the same size.
	stem3(, 'fill') specifies whether to color the interior of the circle at the end of the stem.
	<pre>stem3(,LineSpec) specifies the line style, marker symbol, and color for the stems. See LineSpec for more information.</pre>
	h = stem3() returns handles to stemseries graphics objects.

Examples Create a three-dimensional stem plot to visualize a function of two variables.





See Also bar, plot, stairs, stem

"Discrete Data Plots" on page 1-99 for related functions Stemseries Properties for descriptions of properties Three-Dimensional Stem Plots for more examples

Stemseries Properties

Purpose	Define stemseries properties
Modifying Properties	You can set and query graphics object properties using the set and get commands or with the property editor (propertyeditor).
-	Note that you cannot define default properties for stemseries objects.
	See Plot Objects for information on stemseries objects.
Stemseries Property	This section provides a description of properties. Curly braces $\{\}$ enclose default values.
Descriptions	Annotation hg.Annotation object Read Only
	Control the display of stemseries objects in legends. The Annotation property enables you to specify whether this stemseries object is represented in a figure legend.
	Querying the Annotation property returns the handle of an hg.Annotation object. The hg.Annotation object has a property called LegendInformation, which contains an hg.LegendEntry object.
	Once you have obtained the hg.LegendEntry object, you can set its IconDisplayStyle property to control whether the stemseries object is displayed in a figure legend:
	IconDisplayStyle Purpose Value
	on Include the stemseries object in a legend as one entry, but not its children objects
	off Do not include the stemseries or its children in a legend (default)
	childrenInclude only the children of the stemseries as separate entries in the legend

Setting the IconDisplayStyle Property

These commands set the IconDisplayStyle of a graphics object with handle hobj to children, which causes each child object to have an entry in the legend:

```
hAnnotation = get(hobj,'Annotation');
hLegendEntry = get(hAnnotation,'LegendInformation');
set(hLegendEntry,'IconDisplayStyle','children')
```

Using the IconDisplayStyle Property

See "Controlling Legends" for more information and examples.

BaseLine

handle of baseline

Handle of the baseline object. This property contains the handle of the line object used as the baseline. You can set the properties of this line using its handle. For example, the following statements create a stem plot, obtain the handle of the baseline from the stemseries object, and then set line properties that make the baseline a dashed, red line.

```
stem_handle = stem(randn(10,1));
baseline_handle = get(stem_handle,'BaseLine');
set(baseline_handle,'LineStyle','--','Color','red')
```

BaseValue

y-axis value

Y-axis value where baseline is drawn. You can specify the value along the *y*-axis at which the MATLAB software draws the baseline.

BeingDeleted

on | {off} Read Only

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions might not need to perform actions on objects if the objects are going to be deleted, and therefore, can check the object's BeingDeleted property before acting.

BusyAction

cancel | {queue}

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callbacks. If there is a callback function executing, callbacks invoked subsequently always attempt to interrupt it.

If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are

- cancel Discard the event that attempted to execute a second callback routine.
- queue Queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn

string or function handle

Button press callback function. A callback that executes whenever you press a mouse button while the pointer is over this object, but not over another graphics object. See the HitTestArea property for information about selecting objects of this type.

See the figure's SelectionType property to determine if modifier keys were also pressed.

This property can be

- A string that is a valid MATLAB expression
- The name of a MATLAB file
- A function handle

Set this property to a function handle that references the callback. The expressions execute in the MATLAB workspace.

See "Function Handle Callbacks" for information on how to use function handles to define the callbacks.

Children

array of graphics object handles

Children of the stemseries object. An array containing the handles of all line objects parented to the stemseries object (whether visible or not).

If a child object's HandleVisibility property is callback or off, its handle does not show up in this object's Children property. If you want the handle in the Children property, set the root ShowHiddenHandles property to on. For example:

set(0,'ShowHiddenHandles','on')

Clipping

{on} | off

Clipping mode. MATLAB clips graphs to the axes plot box by default. If you set Clipping to off, portions of graphs can be displayed outside the axes plot box. This can occur if you create a plot object, set hold to on, freeze axis scaling (axis manual), and then create a larger plot object.

Color

ColorSpec

Color of stem lines. A three-element RGB vector or one of the MATLAB predefined names, specifying the line color. See the **ColorSpec** reference page for more information on specifying color.

For example, the following statement would produce a stem plot with red lines.

h = stem(randn(10,1), 'Color', 'r');

CreateFcn

string or function handle

Callback routine executed during object creation. This property defines a callback that executes when MATLAB creates an object. You must specify the callback during the creation of the object. For example,

graphicfcn(y, 'CreateFcn',@CallbackFcn)

where @CallbackFcn is a function handle that references the callback function and graphicfcn is the plotting function which creates this object.

MATLAB executes this routine after setting all other object properties. Setting this property on an existing object has no effect. The handle of the object whose CreateFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DeleteFcn

string or function handle

Callback executed during object deletion. A callback that executes when this object is deleted (e.g., this might happen when you issue a delete command on the object, its parent axes, or the figure containing it). MATLAB executes the callback before destroying the object's properties so the callback routine can query these values.

The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which can be queried using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

See the BeingDeleted property for related information.

DisplayName

string (default is empty string)

String used by legend for this stemseries object. The legend function uses the string defined by the DisplayName property to label this stemseries object in the legend.

- If you specify string arguments with the legend function, DisplayName is set to this stemseries object's corresponding string and that string is used for the legend.
- If DisplayName is empty, legend creates a string of the form, ['data' n], where n is the number assigned to the object

based on its location in the list of legend entries. However, legend does not set DisplayName to this string.

- If you edit the string directly in an existing legend, DisplayName is set to the edited string.
- If you specify a string for the DisplayName property and create the legend using the figure toolbar, then MATLAB uses the string defined by DisplayName.
- To add programmatically a legend that uses the DisplayName string, call legend with the toggle or show option.

See "Controlling Legends" for more examples.

EraseMode

{normal} | none | xor | background

Erase mode. This property controls the technique MATLAB uses to draw and erase objects and their children. Alternative erase modes are useful for creating animated sequences, where control of the way individual objects are redrawn is necessary to improve performance and obtain the desired effect.

- normal Redraw the affected region of the display, performing the three-dimensional analysis necessary to ensure that all objects are rendered correctly. This mode produces the most accurate picture, but is the slowest. The other modes are faster, but do not perform a complete redraw and are therefore less accurate.
- none Do not erase objects when they are moved or destroyed. While the objects are still visible on the screen after erasing with EraseMode none, you cannot print these objects because MATLAB stores no information about their former locations.
- xor Draw and erase the object by performing an exclusive OR (XOR) with each pixel index of the screen behind it. Erasing the object does not damage the color of the objects behind it. However, the color of the erased object depends on the color of

the screen behind it and it is correctly colored only when it is over the axes background color (or the figure background color if the axes Color property is set to none). That is, it isn't erased correctly if there are objects behind it.

• background — Erase the graphics objects by redrawing them in the axes background color, (or the figure background color if the axes Color property is set to none). This damages other graphics objects that are behind the erased object, but the erased object is always properly colored.

Printing with Nonnormal Erase Modes

MATLAB always prints figures as if the EraseMode of all objects is normal. This means graphics objects created with EraseMode set to none, xor, or background can look different on screen than on paper. On screen, MATLAB can mathematically combine layers of colors (e.g., performing an XOR on a pixel color with that of the pixel behind it) and ignore three-dimensional sorting to obtain greater rendering speed. However, these techniques are not applied to the printed output.

Set the axes background color with the axes Color property. Set the figure background color with the figure Color property.

You can use the MATLAB getframe command or other screen capture applications to create an image of a figure containing nonnormal mode objects.

HandleVisibility

{on} | callback | off

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally accessing objects that you need to protect for some reason.

- on Handles are always visible when HandleVisibility is on.
- callback Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have access to object handles.
- off Setting HandleVisibility to off makes handles invisible at all times. This might be necessary when a callback invokes a function that might potentially damage the GUI (such as evaluating a user-typed string) and so temporarily hides its own handles during the execution of that function.

Functions Affected by Handle Visibility

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close.

Properties Affected by Handle Visibility

When a handle's visibility is restricted using callback or off, the object's handle does not appear in its parent's Children property, figures do not appear in the root's CurrentFigure property, objects do not appear in the root's CallbackObject property or in the figure's CurrentObject property, and axes do not appear in their parent's CurrentAxes property.

Overriding Handle Visibility

You can set the root ShowHiddenHandles property to on to make all handles visible regardless of their HandleVisibility settings (this does not affect the values of the HandleVisibility properties). See also findall.

Handle Validity

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties and pass it to any function that operates on handles.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

HitTest

{on} | off

Selectable by mouse click. HitTest determines whether this object can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click on the objects that compose the area graph. If HitTest is off, clicking this object selects the object below it (which is usually the axes containing it).

HitTestArea

on | {off}

Select the object by clicking lines or area of extent. This property enables you to select plot objects in two ways:

- Select by clicking lines or markers (default).
- Select by clicking anywhere in the extent of the plot.

When HitTestArea is off, you must click the object's lines or markers (excluding the baseline, if any) to select the object. When HitTestArea is on, you can select this object by clicking anywhere within the extent of the plot (i.e., anywhere within a rectangle that encloses it). Interruptible
 {on} | off

Callback routine interruption mode. The Interruptible property controls whether an object's callback can be interrupted by callbacks invoked subsequently.

Only callbacks defined for the ButtonDownFcn property are affected by the Interruptible property. MATLAB checks for events that can interrupt a callback only when it encounters a drawnow, figure, getframe, or pause command in the routine. See the BusyAction property for related information.

Setting Interruptible to on allows any graphics object's callback to interrupt callback routines originating from a bar property. Note that MATLAB does not save the state of variables or the display (e.g., the handle returned by the gca or gcf command) when an interruption occurs.

LineStyle

{-} | -- | : | -. | none

Line style. This property specifies the line style of the object. Available line styles are shown in the following table.

Specifier String	Line Style
-	Solid line (default)
	Dashed line
:	Dotted line
	Dash-dot line
none	No line

You can use LineStyle none when you want to place a marker at each point but do not want the points connected with a line (see the Marker property).

LineWidth

scalar

The width of linear objects and edges of filled areas. Specify this value in points (1 point = $1/_{72}$ inch). The default LineWidth is 0.5 points.

Marker

character (see table)

Marker symbol. The Marker property specifies the type of markers that are displayed at plot vertices. You can set values for the Marker property independently from the LineStyle property. Supported markers include those shown in the following table.

Marker Specifier	Description
+	Plus sign
0	Circle
*	Asterisk
	Point
x	Cross
S	Square
d	Diamond
^	Upward-pointing triangle
V	Downward-pointing triangle
>	Right-pointing triangle
<	Left-pointing triangle
р	Five-pointed star (pentagram)

Marker Specifier	Description
h	Six-pointed star (hexagram)
none	No marker (default)

MarkerEdgeColor

ColorSpec | none | {auto}

Marker edge color. The color of the marker or the edge color for filled markers (circle, square, diamond, pentagram, hexagram, and the four triangles). ColorSpec defines the color to use. none specifies no color, which makes nonfilled markers invisible. auto sets MarkerEdgeColor to the same color as the Color property.

MarkerFaceColor

ColorSpec | {none} | auto

Marker face color. The fill color for markers that are closed shapes (circle, square, diamond, pentagram, hexagram, and the four triangles). ColorSpec defines the color to use. none makes the interior of the marker transparent, allowing the background to show through. auto sets the fill color to the axes color, or to the figure color if the axes Color property is set to none (which is the factory default for axes objects).

MarkerSize

size in points

Marker size. A scalar specifying the size of the marker in points. The default value for MarkerSize is 6 points (1 point = 1/72 inch). Note that MATLAB draws the point marker (specified by the '.' symbol) at one-third the specified size.

Parent

handle of parent axes, hggroup, or hgtransform

Parent of this object. This property contains the handle of the object's parent. The parent is normally the axes, hggroup, or hgtransform object that contains the object.

See "Objects That Can Contain Other Objects" for more information on parenting graphics objects.

Selected

on | {off}

Is object selected? When you set this property to on, MATLAB displays selection "handles" at the corners and midpoints if the SelectionHighlight property is also on (the default). You can, for example, define the ButtonDownFcn callback to set this property to on, thereby indicating that this particular object is selected. This property is also set to on when an object is manually selected in plot edit mode.

SelectionHighlight

{on} | off

Objects are highlighted when selected. When the Selected property is on, MATLAB indicates the selected state by drawing four edge handles and four corner handles. When SelectionHighlight is off, MATLAB does not draw the handles except when in plot edit mode and objects are selected manually.

Тад

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when you are constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callbacks.

For example, you might create a stemseries object and set the Tag property:

t = stem(Y, 'Tag', 'stem1')

When you want to access the stemseries object, you can use findobj to find the stemseries object's handle. The following statement changes the MarkerFaceColor property of the object whose Tag is stem1.

```
set(findobj('Tag','stem1'),'MarkerFaceColor','red')
```

Туре

string (read only)

Type of graphics object. This property contains a string that identifies the class of the graphics object. For stemseries objects, Type is 'hggroup'. The following statement finds all the hggroup objects in the current axes object.

t = findobj(gca,'Type','hggroup');

UIContextMenu

handle of a uicontextmenu object

Associate a context menu with this object. Assign this property the handle of a uicontextmenu object created in the object's parent figure. Use the uicontextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click over the object.

UserData

array

User-specified data. This property can be any data you want to associate with this object (including cell arrays and structures). The object does not set values for this property, but you can access it using the set and get functions.

Visible

{on} | off

Visibility of this object and its children. By default, a new object's visibility is on. This means all children of the object are visible unless the child object's Visible property is set to off. Setting an object's Visible property to off prevents the object from being displayed. However, the object still exists and you can set and query its properties.

XData

array

X-axis location of stems. The stem function draws an individual stem at each x-axis location in the XData array. XData can be either a matrix equal in size to YData or a vector equal in length to the number of rows in YData. That is, length(XData) == size(YData,1). XData does not need to be monotonically increasing.

If you do not specify XData (i.e., the input argument x), the stem function uses the indices of YData to create the stem plot. See the XDataMode property for related information.

XDataMode

{auto} | manual

Use automatic or user-specified x-axis values. If you specify XData (by setting the XData property or specifying the x input argument), MATLAB sets this property to manual and uses the specified values to label the x-axis.

If you set XDataMode to auto after having specified XData, MATLAB resets the *x*-axis ticks to 1:size(YData,1) or to the column indices of the ZData, overwriting any previous values for XData.

XDataSource

string (MATLAB variable)

Link XData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the XData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change XData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

YData

scalar, vector, or matrix

Stem plot data. YData contains the data plotted as stems. Each value in YData is represented by a marker in the stem plot. If YData is a matrix, MATLAB creates a series of stems for each column in the matrix.

The input argument y in the stem function calling syntax assigns values to YData.

YDataSource

string (MATLAB variable)

Link YData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the YData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change YData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

ZData

vector of coordinates

Z-coordinates. A data defining the stems for 3-D stem graphs. XData and YData (if specified) must be the same size.

ZDataSource

string (MATLAB variable)

Link ZData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the ZData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change ZData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

Purpose	Stop timer(s)
Syntax	<pre>stop(obj)</pre>
Description	<pre>stop(obj) stops the timer, represented by the timer object, obj. If obj is an array of timer objects, the stop function stops them all. Use the timer function to create a timer object.</pre>
	The stop function sets the Running property of the timer object, obj, to 'off', halts further TimerFcn callbacks, and executes the StopFcn callback.
See Also	timer, start

stopasync

Purpose	Stop asynchronous read and write operations		
Syntax	stopasync(obj)		
Description	<pre>stopasync(obj) stops any asynchronous read or write operation that is in progress for the serial port object, obj.</pre>		
Remarks	You can write data asynchronously using the fprintf or fwrite function. You can read data asynchronously using the readasync function, or by configuring the ReadAsyncMode property to continuous. In-progress asynchronous operations are indicated by the TransferStatus property.		
	If obj is an array of serial port objects and one of the objects cannot be stopped, the remaining objects in the array are stopped and a warning is returned. After an object stops:		
	• Its TransferStatus property is configured to idle.		
	• Its ReadAsyncMode property is configured to manual.		
	• The data in its output buffer is flushed.		
	Data in the input buffer is not flushed. You can return this data to the MATLAB workspace using any of the synchronous read functions. If you execute the readasync function, or configure the ReadAsyncMode property to continuous, then the new data is appended to the existing data in the input buffer.		
See Also	Functions		
	fprintf, fwrite, readasync		
	Properties		
	ReadAsyncMode, TransferStatus		

Purpose	Convert string to double-precision value
Syntax	<pre>X = str2double('str') X = str2double(C)</pre>
Description	X = str2double('str') converts the string str, which should be an ASCII character representation of a real or complex scalar value, to the MATLAB double-precision representation. The string can contain digits, a comma (thousands separator), a decimal point, a leading + or - sign, an e preceding a power of 10 scale factor, and an i for a complex unit.
	If str does not represent a valid scalar value, str2double returns NaN.
	X = str2double(C) converts the strings in the cell array of strings C to double precision. The matrix X returned will be the same size as C.
Examples	Here are some valid str2double conversions.
	<pre>str2double('123.45e7') str2double('123 + 45i') str2double('3.14159') str2double('2.7i - 3.14') str2double({'2.71' '3.1415'}) str2double('1,200.34')</pre>
See Also	char, hex2num, num2str, str2num

str2func

Purpose	Construct function handle from function name string		
Syntax	<pre>str2func('str')</pre>		
Description	<pre>str2func('str') constructs a function handle fhandle for the function named in the string 'str'. The contents of str can be the name of a file that defines a MATLAB function, or the name of an anonymous function.</pre>		
	You can create a function handle fh using any of the following four methods:		
	• Create a handle to a named function:		
	<pre>fh = @functionName; fh = str2func(functionName);</pre>		
	• Create a handle to an anonymous function:		
	<pre>fh = @(x)functionDef(x); fh = str2func('@(x)functionDef(x)');</pre>		
	You can create an array of function handles from strings by creating the handles individually with str2func, and then storing these handles in a cell array.		
Remarks	Nested functions are not accessible to str2func. To construct a function handle for a nested function, you must use the function handle constructor, @.		
	Any variables and their values originally stored in a function handle when it was created are lost if you convert the function handle to a string and back again using the func2str and str2func functions.		
Examples	Example 1		
	To convert the string, 'sin', into a handle for that function, type		
	<pre>fh = str2func('sin')</pre>		

fh = @sin

Example 2

If you pass a function name string in a variable, the function that receives the variable can convert the function name to a function handle using str2func. The example below passes the variable, funcname, to function makeHandle, which then creates a function handle. Here is the function:

function fh = makeHandle(funcname)
fh = str2func(funcname);

This is the code that calls makeHandle to construct the function handle:

```
makeHandle('sin')
ans =
    @sin
```

Example 3

To call str2func on a cell array of strings, use the cellfun function. This returns a cell array of function handles:

Example 4

In the following example, the myminbnd function expects to receive either a function handle or string in the first argument. If you pass a string, myminbnd constructs a function handle from it using str2func, and then uses that handle in a call to fminbnd:

```
function myminbnd(fhandle, lower, upper)
if ischar(fhandle)
```

```
disp 'converting function string to function handle ...'
fhandle = str2func(fhandle);
end
fminbnd(fhandle, lower, upper)
```

Whether you call myminbnd with a function handle or function name string, the function can handle the argument appropriately:

```
myminbnd('humps', 0.3, 1)
converting function string to function handle ...
ans =
      0.6370
```

Example 5

The dirByType function shown here creates an anonymous function called dirCheck. What the anonymous function does depends upon the value of the dirType argument passed in to the primary function. The example demonstrates one possible use of str2func with anonymous functions:

```
function dirByType(dirType)
switch(dirType)
   case 'class', leadchar = '@';
   case 'package', leadchar = '+';
   otherwise disp('ERROR: Unrecognized type'), return;
end
dirfile = @(fs)isdir(fs.name);
dirCheckStr = ['@(fs)strcmp(fs.name(1,1),''', leadchar, ''')'];
dirCheckFun = str2func(dirCheckStr);
         filecount = length(s);
s = dir;
for k=1:filecount
   fstruct = s(k);
   if dirfile(fstruct) && dirCheckFun(fstruct)
       fprintf('%s folder: %s\n', dirType, fstruct.name)
   end
end
```

Generate a list of class and package folders:

dirByType('class')
class folder: @Point
class folder: @asset
class folder: @bond
dirByType('package')
package folder: +containers
package folder: +event
package folder: +mypkg

See Also function_handle, func2str, functions

str2mat

Purpose	Form blank-pa	added charac	ter matrix fro	om strings
	Note str2ma	t will be rem	oved in a fut	ure version. Use char instead.
Syntax	S = str2mat((T1, T2, T3,)	
Description	text strings T pads each stri parameter, Ti	1, T2, T3, ng with blanl , can itself be	as rows. ts in order to a string mat	the matrix S containing the The function automatically form a valid matrix. Each text trix. This allows the creation of strings are significant.
Remarks	str2mat differ in the output.			npty strings produce blank rows s are ignored.
Examples	x = str2m	at('36842',	'39751' , '	38453', '90307');
	whos x Name	Size	Bytes	Class
	x	4x5	40	char array
	x(2,3)			
	ans =			
	7			
See Also	char			

Purpose	Convert string to number
Syntax	x = str2num('str') [x, status] = str2num('str')
Description	

Note str2num uses the eval function to convert the input argument. Side effects can occur if the string contains calls to functions. Using str2double can avoid some of these side effects.

x = str2num('str') converts the string str, which is an ASCII character representation of a numeric value, to numeric representation. str2num also converts string matrices to numeric matrices. If the input string does not represent a valid number or matrix, str2num(str) returns the empty matrix in x.

The input string can contain one or more numbers separated by spaces, commas, or semicolons, such as '5', '10,11,12', or '5,10;15,20'. In addition to numerical values and delimiters, the input string can also include a decimal point, leading + or - signs, the letter e or d preceding a power of 10 scale factor, or the letter i or j indicating a complex or imaginary number.

The following table shows several examples of valid inputs to str2num:

String Input	Numeric Output	Output Class
' 500 '	500	1-by-1 scalar double
'500 250 125 67'	500, 250, 125, 67	1-by-4 row vector of double
'500; 250; 125; 62.5'	$500.0000 \\ 250.0000 \\ 125.0000 \\ 62.5000$	4-by-1 column vector of double

String Input	Numeric Output	Output Class
'1 23 6 21; 53:56'	$\begin{array}{rrrrrrrrrrrrrrrrrrrrrrrrrrrrrrrrrrrr$	2-by-5 matrix of double
'12e-3 5.9e-3'	$0.0120\ 0.0059$	vector of double
'uint16(500)'	500	16-bit unsigned integer

If the input string does not represent a valid number or matrix, str2num(str) returns the empty matrix in x.

[x, status] = str2num('str') returns the status of the conversion in logical status, where status equals logical 1 (true) if the conversion succeeds, and logical 0 (false) otherwise.

Space characters can be significant. For instance, str2num('1+2i')and str2num('1 + 2i') produce x = 1+2i, while str2num('1 + 2i')produces $x = [1 \ 2i]$. You can avoid these problems by using the str2double function.

Examples Input a character string that contains a single number. The output is a scalar double:

```
A = str2num('500')
A =
    500
class(A)
ans =
    double
```

Repeat this operation, but this time using an unsigned 16-bit integer:

ans = uint16

Try three different ways of specifying a row vector. Each returns the same answer:

```
str2num('2 4 6 8')
                                 % Separate with spaces.
ans =
     2
           4
               6
                       8
str2num('2,4,6,8')
                                 % Separate with commas.
ans =
     2
           4
                 6
                       8
str2num('[2 4 6 8]')
                                 % Enclose in brackets.
ans =
     2
           4
                 6
                       8
```

Note that the first two of these commands do not need the MATLAB square bracket operator to create a matrix. The str2num function inserts the brackets for you if they are needed.

Use a column vector this time:

```
str2num('2; 4; 6; 8')
ans =
2
4
6
8
```

And now a 2-by-2 matrix:

```
str2num('2 4; 6 8')
ans =
2 4
6 8
```

See Also num2str, str2double, hex2num, sscanf, sparse, char, special characters

Purpose	Concatenate strings horizontally		
Syntax	<pre>combinedStr = strcat(s1, s2,, sN)</pre>		
Description	combinedStr = strcat(s1, s2,, sN) horizontally concatenates strings in arrays $s1, s2,, sN$. Inputs can be combinations of single strings, strings in scalar cells, character arrays with the same number of rows, and same-sized cell arrays of strings. If any input is a cell array, $combinedStr$ is a cell array of strings. Otherwise, $combinedStr$ is a character array.		
Tips	 For character array inputs, strcat removes trailing ASCII white-space characters: space, tab, vertical tab, newline, carriage return, and form-feed. To preserve trailing spaces when concatenating character arrays, use horizontal array concatenation, [s1, s2,, sN]. See the final example in the following section. For cell array inputs, strcat does not remove trailing white space. When combining nonscalar cell arrays and multi-row character arrays, cell arrays must be column vectors with the same number of rows as the character arrays. 		
Examples	<pre>Concatenate two cell arrays: a = {'abcde', 'fghi'}; b = {'jkl', 'mn'}; ab = strcat(a, b) MATLAB returns ab = 'abcdejkl' 'fghimn'</pre>		

Combine cell arrays ${\tt a}$ and ${\tt b}$ from the previous example with a scalar cell:

Compare the use of strcat and horizontal array concatenation with strings that contain trailing spaces:

```
a = 'hello ';
b = 'goodbye';
using_strcat = strcat(a, b)
using_arrayop = [a, b] % Equivalent to horzcat(a, b)
MATLAB returns
using_strcat =
hellogoodbye
using_arrayop =
hello goodbye
```

Purpose	Compare strings
Syntax	<pre>TF = strcmp('str1', 'str2') TF = strcmp('str', C) TF = strcmp(C1, C2)</pre>
	Each of these syntaxes applies to both strcmp and strcmpi. The strcmp function is case sensitive in matching strings, while strcmpi is not.
Description	Although the following descriptions show only strcmp, they apply to strcmpi as well. The two functions are the same except that strcmpi compares strings without sensitivity to letter case:
	TF = strcmp('str1', 'str2') compares the strings str1 and str2 and returns logical 1 (true) if they are identical, and returns logical 0 (false) otherwise. str1 and str2 can be character arrays of any dimension, but strcmp does not return true unless the sizes of both arrays are equal, and the contents of the two arrays are the same.
	TF = strcmp('str', C) compares string str to the each element of cell array C, where str is a character vector (or a 1-by-1 cell array) and C is a cell array of strings. The function returns TF , a logical array that is the same size as C and contains logical 1 (true) for those elements of C that are a match, and logical 0 (false) for those elements that are not. The order of the first two input arguments is not important.
	TF = strcmp(C1, C2) compares each element of C1 to the same element in C2, where C1 and C2 are equal-size cell arrays of strings. Input C1 or C2 can also be a character array with the right number of rows. The function returns TF, a logical array that is the same size as C1 and C2, and contains logical 1 (true) for those elements of C1 and C2 that are a match, and logical 0 (false) for those elements that are not.
Remarks	These functions are intended for comparison of character data. When used to compare numeric data, they return logical 0 .
	Any leading and trailing blanks in either of the strings are explicitly included in the comparison.

The value returned by strcmp and strcmpi is not the same as the C language convention.

strcmp and strcmpi support international character sets.

Examples Example 1

Perform a simple comparison of two strings:

Example 2

Create 3 cell arrays of strings:

Compare cell arrays A and B with sensitivity to case:

```
strcmp(A, B)
ans =
0 0
1 1
```

Compare cell arrays B and C without sensitivity to case. Note that 'Toolboxes' doesn't match because of the leading space characters in $C{2,1}$ that do not appear in $B{2,1}$:

```
strcmpi(B, C)
ans =
1 0
0 1
```

Example 3

Compare a string vector to a cell array of strings, a string vector to a string array, and a string array to a cell array of strings. Start by creating a cell array of strings (cellArr), a string array containing the same strings plus space characters for padding s(strArr), and a string vector containing one of the strings plus padding (strVec):

```
cellArr = { ...
    'There are 10 kinds of people in the world,'; ...
    'those who understand binary math,'; ...
    'and those who don''t.'};
strArr = char(cellArr);
strVec = strArr(2,:)
strVec =
    those who understand binary math,
```

Remove the space padding from the string vector and compare it to the cell array. The MATLAB software compares the string with each row of the cell array, finding a match on the second row:

Compare the string vector with the string array. Unlike the case above, MATLAB does not compare the string vector with each row of the string array. It compares the entire contents of one against the entire contents of the other:

```
strcmp(strVec, strArr)
```

strcmp, strcmpi

ans = 0

Lastly, compare each row of the three-row string array against the same rows of the cell array. MATLAB finds them all to be equivalent. Note that in this case you do not have to remove the space padding from the string array:

```
strcmp(strArr, cellArr)
ans =
    1
    1
    1
    1
```

See Also strncmp, strncmpi, strfind, regexp, regexpi, regexprep, regexptranslate

Purpose	Compute 2-D streamline data
Syntax	<pre>XY = stream2(x,y,u,v,startx,starty) XY = stream2(u,v,startx,starty) XY = stream2(,options)</pre>
Description	XY = stream2(x,y,u,v,startx,starty) computes streamlines from vector data u and v. The arrays x and y define the coordinates for u and v and must be monotonic and 2-D plaid (such as the data produced by meshgrid). startx and starty define the starting positions of the streamlines. The section "Specifying Starting Points for Stream Plots" provides more information on defining starting points.
	The returned value XY contains a cell array of vertex arrays.
	XY = stream2(u,v,startx,starty) assumes the arrays x and y are defined as [x,y] = meshgrid(1:n,1:m) where [m,n] = size(u).
	XY = stream2(,options) specifies the options used when creating the streamlines. Define options as a one- or two-element vector containing the step size or the step size and the maximum number of vertices in a streamline:
	[stepsize]
	or
	[stepsize, max_number_vertices]
	If you do not specify a value, MATLAB software uses the default:
	 Step size = 0.1 (one tenth of a cell) Maximum number of vertices = 10000
	Use the streamline command to plot the data returned by stream2.
Examples	This example draws 2-D streamlines from data representing air currents over regions of North America.

stream2

See Also

load wind
[sx,sy] = meshgrid(80,20:10:50);
streamline(stream2(x(:,:,5),y(:,:,5),u(:,:,5),v(:,:,5),sx,sy));
coneplot, stream3, streamline
"Volume Visualization" on page 1-111 for related functions
Specifying Starting Points for Stream Plots for related information

Purpose	Compute 3-D streamline data
Syntax	<pre>XYZ = stream3(X,Y,Z,U,V,W,startx,starty,startz) XYZ = stream3(U,V,W,startx,starty,startz) XYZ = stream3(,options)</pre>
Description	XYZ = stream3(X,Y,Z,U,V,W,startx,starty,startz) computes streamlines from vector data U, V, W. The arrays X, Y, Z define the coordinates for U, V, W and must be monotonic and 3-D plaid (such as the data produced by meshgrid). startx, starty, and startz define the starting positions of the streamlines. The section "Specifying Starting Points for Stream Plots" provides more information on defining starting points.
	The returned value XYZ contains a cell array of vertex arrays.
	<pre>XYZ = stream3(U,V,W,startx,starty,startz) assumes the arrays X,Y, and Z are defined as [X,Y,Z] = meshgrid(1:N,1:M,1:P) where [M,N,P] = size(U).</pre>
	XYZ = stream3(,options) specifies the options used when creating the streamlines. Define options as a one- or two-element vector containing the step size or the step size and the maximum number of vertices in a streamline:
	[stepsize]
	or
	[stepsize, max_number_vertices]
	If you do not specify values, MATLAB software uses the default:
	• Step size = 0.1 (one tenth of a cell)
	• Maximum number of vertices = 10000
	Use the streamline command to plot the data returned by stream3.

stream3

Examples	This example draws 3-D streamlines from data representing air currents over regions of North America.	
	<pre>load wind [sx sy sz] = meshgrid(80,20:10:50,0:5:15); streamline(stream3(x,y,z,u,v,w,sx,sy,sz)) view(3)</pre>	
See Also	coneplot, stream2, streamline	
	"Volume Visualization" on page 1-111 for related functions	
	Specifying Starting Points for Stream Plots for related information	

Purpose	Plot streamlines from 2-D or 3-D vector data
	51
GUI Alternatives	To graph selected variables, use the Plot Selector Pot(t,y) • in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.
Syntax	<pre>streamline(X,Y,Z,U,V,W,startx,starty,startz) streamline(U,V,W,startx,starty,startz) streamline(XYZ) streamline(X,Y,U,V,startx,starty) streamline(U,V,startx,starty) streamline(XY) streamline(,options) streamline(axes_handle,) h = streamline()</pre>
Description	streamline(X,Y,Z,U,V,W,startx,starty,startz) draws streamlines from 3-D vector data U, V, W. The arrays X, Y, Z define the coordinates for U, V, W and must be monotonic and 3-D plaid (such as the data produced by meshgrid). startx, starty, startz define the starting positions of the streamlines. The section Specifying Starting Points for Stream Plots provides more information on defining starting points.
	<pre>streamline(U,V,W,startx,starty,startz) assumes the arrays X, Y, and Z are defined as [X,Y,Z] = meshgrid(1:N,1:M,1:P), where [M,N,P] = size(U).</pre>
	<pre>streamline(XYZ) assumes XYZ is a precomputed cell array of vertex arrays (as produced by stream3).</pre>

streamline(X,Y,U,V,startx,starty) draws streamlines from 2-D
vector data U, V. The arrays X, Y define the coordinates for U, V and must
be monotonic and 2-D plaid (such as the data produced by meshgrid).
startx and starty define the starting positions of the streamlines.
The output argument h contains a vector of line handles, one handle
for each streamline.

```
streamline(U,V,startx,starty) assumes the arrays X and Y are
defined as [X,Y] = meshgrid(1:N,1:M), where [M,N] = size(U).
```

streamline(XY) assumes XY is a precomputed cell array of vertex
arrays (as produced by stream2).

streamline(...,options) specifies the options used when creating the streamlines. Define options as a one- or two-element vector containing the step size or the step size and the maximum number of vertices in a streamline:

[stepsize]

or

[stepsize, max number vertices]

If you do not specify values, MATLAB uses the default:

- Step size = 0.1 (one tenth of a cell)
- Maximum number of vertices = 1000

streamline(axes_handle,...) plots into the axes object with the handle axes_handle instead of the into current axes object (gca).

h = streamline(...) returns a vector of line handles, one handle for each streamline.

Examples This example draws streamlines from data representing air currents over a region of North America. Loading the wind data set creates the variables x, y, z, u, v, and w in the MATLAB workspace.

The plane of streamlines indicates the flow of air from the west to the east (the x-direction) beginning at x = 80 (which is close to the minimum value of the x coordinates). The y- and z-coordinate starting points are multivalued and approximately span the range of these coordinates. meshgrid generates the starting positions of the streamlines.

```
load wind
[sx,sy,sz] = meshgrid(80,20:10:50,0:5:15);
h = streamline(x,y,z,u,v,w,sx,sy,sz);
set(h,'Color','red')
view(3)
```

See Alsoconeplot, stream2, stream3, streamparticles"Volume Visualization" on page 1-111 for related functionsSpecifying Starting Points for Stream Plots for related information

Stream Line Plots of Vector Data for another example

streamparticles

Purpose	Plot stream particles	
GUI Alternatives	To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.	
Syntax	<pre>streamparticles(vertices) streamparticles(vertices,n) streamparticles(,'PropertyName',PropertyValue,) streamparticles(line_handle,) h = streamparticles()</pre>	
Description	streamparticles(vertices) draws stream particles of a vector field. Stream particles are usually represented by markers and can show the position and velocity of a streamline. vertices is a cell array of 2-D or 3-D vertices (as if produced by stream2 or stream3).	
	<pre>streamparticles(vertices,n) uses n to determine how many stream particles to draw. The ParticleAlignment property controls how n is interpreted.</pre>	
	• If ParticleAlignment is set to off (the default) and n is greater than 1, approximately n particles are drawn evenly spaced over the streamline vertices.	
	If n is less than or equal to 1, n is interpreted as a fraction of the original stream vertices; for example, if n is 0.2 , approximately 20% of the vertices are used.	
	n determines the upper bound for the number of particles drawn. The actual number of particles can deviate from n by as much as a factor of 2.	

• If ParticleAlignment is on, n determines the number of particles on the streamline having the most vertices and sets the spacing on the other streamlines to this value. The default value is n = 1.

streamparticles(..., 'PropertyName', PropertyValue,...)
controls the stream particles using named properties and specified
values. Any unspecified properties have default values. MATLAB
ignores the case of property names.

Stream Particle Properties

Animate — Stream particle motion [nonnegative integer]

The number of times to animate the stream particles. The default is 0, which does not animate. Inf animates until you enter **Ctrl+C**.

FrameRate — Animation frames per second [nonnegative integer]

This property specifies the number of frames per second for the animation. Inf, the default, draws the animation as fast as possible. Note that the speed of the animation might be limited by the speed of the computer. In such cases, the value of FrameRate cannot necessarily be achieved.

ParticleAlignment — Align particles with streamlines [on | {off}]

Set this property to on to draw particles at the beginning of each streamline. This property controls how streamparticles interprets the argument n (number of stream particles).

Stream particles are line objects. In addition to stream particle properties, you can specify any line object property, such as Marker and EraseMode. streamparticles sets the following line properties when called.

Line Property	Value Set by streamparticles
EraseMode	xor
LineStyle	none
Marker	0

Line Property	Value Set by streamparticles
MarkerEdgeColor	none
MarkerFaceColor	red

You can override any of these properties by specifying a property name and value as arguments to streamparticles. For example, this statement uses RGB values to set the MarkerFaceColor to medium gray:

```
streamparticles(vertices, 'MarkerFaceColor', [.5 .5 .5])
```

streamparticles(line_handle,...) uses the line object identified
by line_handle to draw the stream particles.


h = streamparticles(...) returns a vector of handles to the line objects it creates.

Examples

This example combines streamlines with stream particle animation. The interpstreamspeed function determines the vertices along the streamlines where stream particles will be drawn during the animation, thereby controlling the speed of the animation. Setting the axes DrawMode property to fast provides faster rendering.

```
load wind
[sx sy sz] = meshgrid(80,20:1:55,5);
verts = stream3(x,y,z,u,v,w,sx,sy,sz);
sl = streamline(verts);
iverts = interpstreamspeed(x,y,z,u,v,w,verts,.025);
axis tight; view(30,30); daspect([1 1 .125])
camproj perspective; camva(8)
set(gca, 'DrawMode', 'fast')
box on
streamparticles(iverts,35, 'animate',10, 'ParticleAlignment', 'on')
```

The following picture is a static view of the animation.



This example uses the streamlines in the z = 5 plane to animate the flow along these lines with streamparticles.

```
load wind
daspect([1 1 1]); view(2)
[verts averts] = streamslice(x,y,z,u,v,w,[],[],[5]);
sl = streamline([verts averts]);
axis tight off;
set(sl,'Visible','off')
iverts = interpstreamspeed(x,y,z,u,v,w,verts,.05);
set(gca,'DrawMode','fast','Position',[0 0 1 1],'ZLim',[4.9 5.1])
set(gcf,'Color','black')
streamparticles(iverts, 200, ...
'Animate',100,'FrameRate',40, ...
'MarkerSize',10,'MarkerFaceColor','yellow')
interpstreamspeed, stream3, streamline
```

"Volume Visualization" on page 1-111 for related functions

Creating Stream Particle Animations for more details

See Also

Specifying Starting Points for Stream Plots for related information

streamribbon

Purpose 3-D stream ribbon plot from vector volume data



GUI Alternatives	To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.
Syntax	<pre>streamribbon(X,Y,Z,U,V,W,startx,starty,startz) streamribbon(U,V,W,startx,starty,startz) streamribbon(vertices,X,Y,Z,cav,speed) streamribbon(vertices,cav,speed) streamribbon(vertices,twistangle) streamribbon(,width) streamribbon(axes_handle,) h = streamribbon()</pre>
Description	<pre>streamribbon(X,Y,Z,U,V,W,startx,starty,startz) draws stream ribbons from vector volume data U, V, W. The arrays X, Y, Z define the coordinates for U, V, W and must be monotonic and 3-D plaid (as if produced by meshgrid). startx, starty, and startz define the starting positions of the stream ribbons at the center of the ribbons. The section Specifying Starting Points for Stream Plots provides more information on defining starting points.</pre>
	The twist of the ribbons is proportional to the curl of the vector field. The width of the ribbons is calculated automatically.
	streamribbon(U,V,W,startx,starty,startz) assumes X, Y, and Z are determined by the expression
	[X,Y,Z] = meshgrid(1:n,1:m,1:p)

where [m,n,p] = size(U).

streamribbon(vertices,X,Y,Z,cav,speed) assumes precomputed streamline vertices, curl angular velocity, and flow speed. vertices is a cell array of streamline vertices (as produced by stream3). X, Y, Z, cav, and speed are 3-D arrays.

streamribbon(vertices, cav, speed) assumes X, Y, and Z are determined by the expression

[X,Y,Z] = meshgrid(1:n,1:m,1:p)

where [m,n,p] = size(cav).

streamribbon(vertices, twistangle) uses the cell array of vectors twistangle for the twist of the ribbons (in radians). The size of each corresponding element of vertices and twistangle must be equal.

streamribbon(...,width) sets the width of the ribbons to width.


streamribbon(axes_handle,...) plots into the axes object with the handle axes_handle instead of into the current axes object (gca).

h = streamribbon(...) returns a vector of handles (one per start point) to surface objects.

Examples

This example uses stream ribbons to indicate the flow in the wind data set. Inputs include the coordinates, vector field components, and starting location for the stream ribbons.


```
load wind
[sx sy sz] = meshgrid(80,20:10:50,0:5:15);
streamribbon(x,y,z,u,v,w,sx,sy,sz);
% Define viewing and lighting
axis tight
shading interp;
view(3);
camlight; lighting gouraud
```



This example uses precalculated vertex data (stream3), curl average velocity (curl), and speed $\sqrt{u^2 + v^2 + w^2}$. Using precalculated data enables you to use values other than those calculated from the single data source. In this case, the speed is reduced by a factor of 10 compared to the previous example.

load wind


```
[sx sy sz] = meshgrid(80,20:10:50,0:5:15);
verts = stream3(x,y,z,u,v,w,sx,sy,sz);
cav = curl(x,y,z,u,v,w);
spd = sqrt(u.^2 + v.^2 + w.^2).*.1;
streamribbon(verts,x,y,z,cav,spd);
% Define viewing and lighting
axis tight
shading interp
view(3)
camlight; lighting gouraud
```



This example specifies a twist angle for the stream ribbon.

```
t = 0:.15:15;
verts = {[cos(t)' sin(t)' (t/3)']};
twistangle = {cos(t)'};
streamribbon(verts,twistangle);
% Define viewing and lighting
axis tight
```

shading interp; view(3); camlight; lighting gouraud




This example combines cone plots (coneplot) and stream ribbon plots in one graph.

% Define 3-D arrays x, y, z, u, v, w

```
xmin = -7; xmax = 7;
ymin = -7; ymax = 7;
zmin = -7; zmax = 7;
x = linspace(xmin, xmax, 30);
y = linspace(ymin,ymax,20);
z = linspace(zmin,zmax,20);
[x y z] = meshgrid(x,y,z);
u = y; v = -x; w = 0*x+1;
[cx cy cz] = meshgrid(linspace(xmin,xmax,30),...
linspace(ymin,ymax,30),[-3 4]);
h = coneplot(x,y,z,u,v,w,cx,cy,cz,'quiver');
set(h,'color','k');
% Plot two sets of streamribbons
[sx sy sz] = meshgrid([-1 0 1],[-1 0 1],-6);
streamribbon(x,y,z,u,v,w,sx,sy,sz);
[sx sy sz] = meshgrid([1:6],[0],-6);
streamribbon(x,y,z,u,v,w,sx,sy,sz);
% Define viewing and lighting
shading interp
view(-30,10) ; axis off tight
camproj perspective; camva(66); camlookat;
camdolly(0,0,.5,'fixtarget')
camlight
```

streamribbon



See Alsocurl, streamtube, streamline, stream3"Volume Visualization" on page 1-111 for related functionsDisplaying Curl with Stream Ribbons for another exampleSpecifying Starting Points for Stream Plots for related information

Purpose Plot streamlines in slice planes **Syntax** streamslice(X,Y,Z,U,V,W,startx,starty,startz) streamslice(U,V,W,startx,starty,startz) streamslice(X,Y,U,V) streamslice(U,V) streamslice(...,density) streamslice(..., 'arrowsmode') streamslice(..., 'method') streamslice(axes handle,...) h = streamslice(...) [vertices arrowvertices] = streamslice(...) **Description** streamslice(X,Y,Z,U,V,W,startx,starty,startz) draws well-spaced streamlines (with direction arrows) from vector data U, V, W in axis aligned x-, y-, z-planes starting at the points in the vectors startx, starty, startz. (The section Specifying Starting Points for Stream Plots provides more information on defining starting points.) The arrays X, Y, Z define the coordinates for U, V, W and must be monotonic and 3-D plaid (as if produced by meshgrid). U, V, W must be m-by-n-by-p volume arrays. Do not assume that the flow is parallel to the slice plane. For example, in a stream slice at a constant z, the z component of the vector field W is ignored when you are calculating the streamlines for that plane. Stream slices are useful for determining where to start streamlines, stream tubes, and stream ribbons. streamslice(U,V,W,startx,starty,startz) assumes X, Y, and Z are determined by the expression [X,Y,Z] = meshgrid(1:n,1:m,1:p)where [m, n, p] = size(U).

streamslice(X,Y,U,V) draws well-spaced streamlines (with direction arrows) from vector volume data U, V. The arrays X, Y define the coordinates for U, V and must be monotonic and 2-D plaid (as if produced by meshgrid).

 $\ensuremath{\mathsf{streamslice}}(U,V)$ assumes X, Y, and Z are determined by the expression

[X,Y,Z] = meshgrid(1:n,1:m,1:p)

where [m,n,p] = size(U).

streamslice(...,density) modifies the automatic spacing of the streamlines. density must be greater than 0. The default value is 1; higher values produce more streamlines on each plane. For example, 2 produces approximately twice as many streamlines, while 0.5 produces approximately half as many.

streamslice(..., 'arrowsmode') determines if direction arrows are
present or not. arrowmode can be

- arrows Draw direction arrows on the streamlines (default).
- noarrows Do not draw direction arrows.

streamslice(...,'method') specifies the interpolation method to
use. method can be

- linear Linear interpolation (default)
- cubic Cubic interpolation
- nearest Nearest-neighbor interpolation

See interp3 for more information on interpolation methods.


streamslice(axes_handle,...) plots into the axes object with the handle axes_handle instead of into the current axes object (gca).

h = streamslice(...) returns a vector of handles to the line objects created.

[vertices arrowvertices] = streamslice(...) returns two cell arrays of vertices for drawing the streamlines and the arrows. You can pass these values to any of the streamline drawing functions (streamline, streamribbon, streamtube).

Examples This example creates a stream slice in the wind data set at z = 5.


load wind
streamslice(x,y,z,u,v,w,[],[],[5])
axis tight



This example uses streamslice to calculate vertex data for the streamlines and the direction arrows. This data is then used by streamline to plot the lines and arrows. Slice planes illustrating with color the wind speed $\sqrt{u^2 + v^2 + w^2}$ are drawn by slice in the same planes.

load wind


```
[verts averts] = streamslice(u,v,w,10,10,10);
streamline([verts averts])
spd = sqrt(u.^2 + v.^2 + w.^2);
hold on;
slice(spd,10,10,10);
colormap(hot)
shading interp
view(30,50); axis(volumebounds(spd));
camlight; material([.5 1 0])
```



This example superimposes contour lines on a surface and then uses streamslice to draw lines that indicate the gradient of the surface. interp2 is used to find the points for the lines that lie on the surface.

```
z = peaks;
surf(z)
shading interp
hold on
```

```
[c ch] = contour3(z,20); set(ch,'edgecolor','b')
[u v] = gradient(z);
h = streamslice(-u,-v);
set(h,'color','k')
for i=1:length(h);
zi = interp2(z,get(h(i),'xdata'),get(h(i),'ydata'));
set(h(i),'zdata',zi);
end
view(30,50); axis tight
```



GUI Alternatives To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in *plot edit* mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.

See Also contourslice, slice, streamline, volumebounds "Volume Visualization" on page 1-111 for related functions Specifying Starting Points for Stream Plots for related information

Purpose	Create 3-D stream tube plot
---------	-----------------------------



Syntax	<pre>streamtube(X,Y,Z,U,V,W,startx,starty,startz) streamtube(U,V,W,startx,starty,startz)</pre>
	<pre>streamtube(vertices,X,Y,Z,divergence)</pre>
	<pre>streamtube(vertices,divergence)</pre>
	<pre>streamtube(vertices,width)</pre>
	<pre>streamtube(vertices)</pre>
	<pre>streamtube(,[scale n])</pre>
	<pre>streamtube(axes_handle,)</pre>
	h = streamtube(z)

Description streamtube(X,Y,Z,U,V,W,startx,starty,startz) draws stream tubes from vector volume data U, V, W. The arrays X, Y, Z define the coordinates for U, V, W and must be monotonic and 3-D plaid (as if produced by meshgrid). startx, starty, and startz define the starting positions of the streamlines at the center of the tubes. The section Specifying Starting Points for Stream Plots provides more information on defining starting points.

The width of the tubes is proportional to the normalized divergence of the vector field.

streamtube(U,V,W,startx,starty,startz) assumes X, Y, and Z are determined by the expression

```
[X,Y,Z] = meshgrid(1:n,1:m,1:p)
```

```
where [m,n,p] = size(U).
```

streamtube(vertices,X,Y,Z,divergence) assumes precomputed streamline vertices and divergence. vertices is a cell array of streamline vertices (as produced by stream3). X, Y, Z, and divergence are 3-D arrays. streamtube(vertices,divergence) assumes $X,\,Y,\,{\rm and}\,\,Z$ are determined by the expression

```
[X,Y,Z] = meshgrid(1:n,1:m,1:p)
```

```
where [m,n,p] = size(divergence).
```

streamtube(vertices,width) specifies the width of the tubes in the cell array of vectors, width. The size of each corresponding element of vertices and width must be equal. width can also be a scalar, specifying a single value for the width of all stream tubes.

streamtube(vertices) selects the width automatically.


streamtube(...,[scale n]) scales the width of the tubes by scale. The default is scale = 1. When the stream tubes are created, using start points or divergence, specifying scale = 0 suppresses automatic scaling. n is the number of points along the circumference of the tube. The default is n = 20.

streamtube(axes_handle,...) plots into the axes object with the handle axes handle instead of into the current axes object (gca).

h = streamtube(...z) returns a vector of handles (one per start point) to surface objects used to draw the stream tubes.

Examples This example uses stream tubes to indicate the flow in the wind data set. Inputs include the coordinates, vector field components, and starting location for the stream tubes.


```
load wind
[sx sy sz] = meshgrid(80,20:10:50,0:5:15);
streamtube(x,y,z,u,v,w,sx,sy,sz);
% Define viewing and lighting
view(3)
axis tight
shading interp;
camlight; lighting gouraud
```



This example uses precalculated vertex data (stream3) and divergence (divergence).

```
load wind
[sx sy sz] = meshgrid(80,20:10:50,0:5:15);
verts = stream3(x,y,z,u,v,w,sx,sy,sz);
div = divergence(x,y,z,u,v,w);
streamtube(verts,x,y,z,-div);
```

% Define viewing and lighting view(3) axis tight shading interp camlight; lighting gouraud



streamtube

-

GUI Alternatives	To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipula graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser is the MATLAB Desktop Tools documentation.	
See Also	divergence, streamribbon, streamline, stream3	
	"Volume Visualization" on page 1-111 for related functions	
	Displaying Divergence with Stream Tubes for another example	
	Specifying Starting Points for Stream Plots for related information	

strfind

Purpose	Find one string within another				
Syntax	k = strfind(str, pattern) k = strfind(cellstr, pattern)				
Description	<pre>k = strfind(str, pattern) searches the string str for occurrences of a shorter string, pattern, and returns the starting index of each such occurrence in the double array k. If pattern is not found in str, or if pattern is longer than str, then strfind returns the empty array [].</pre>				
	<pre>k = strfind(cellstr, pattern) searches each string in cell array of strings cellstr for occurrences of a shorter string, pattern, and returns the starting index of each such occurrence in cell array k. If pattern is not found in a string or if pattern is longer then all strings in the cell array, then strfind returns the empty array [], for that string in the cell array.</pre>				
Tips	• The search performed by strfind is case sensitive.				
	• Any leading and trailing blanks in pattern or in the strings being searched are explicitly included in the comparison.				
	• The strfind function does not find empty strings ('') within a string.				
Examples	Use strfind to find a two-letter pattern in string S:				
	S = 'Find the starting indices of the pattern string'; strfind(S, 'in') ans = 2 15 19 45				
	strfind(S, 'In') ans = []				
	<pre>strfind(S, ' ') and -</pre>				
	ans = 5 9 18 26 29 33 41				

Use strfind on a cell array of strings:

cstr = {'How much wood would a woodchuck chuck'; 'if a woodchuck could chuck wood?'}; idx = strfind(cstr, 'wood'); idx{:,:} ans = 10 23 ans = 6 28

This means that 'wood' occurs at indices 10 and 23 in the first string and at indices 6 and 28 in the second.

See Also strtok, strcmp, strncmp, strcmpi, strncmpi, regexp, regexpi, regexprep

strings

Purpose	String handling
Syntax	<pre>S = 'Any Characters' S = [S1 S2] C = {S1 S2} S = strcat(S1, S2,) S = char(S1, S2,) S = char(X) X = double(S)</pre>
Description	S = 'Any Characters' creates a character array, or string. The string is actually a vector that contains the numeric codes for the characters (codes 0 to 127 are ASCII). The length of S is the number of characters. A quotation within the string is indicated by two quotation marks.
	S = [S1 S2] concatenates character arrays S1, S2, etc. into a new character array, S.
	$C = \{S1 \ S2 \ \ldots\}$ creates a cell array of strings. Separate each row of the cell array with a semicolon (;).
	S = strcat(S1, S2,) horizontally concatenates S1, S2, etc., which can be character arrays or cell arrays of strings. If the inputs are character arrays, strcat removes trailing white space. For more information, see the strcat reference page.
	S = char(S1, S2,) vertically concatenates character arrays $S1$, $S2$, etc., padding each input string as needed so that each row contains the same number of characters.
	S = char(X) converts an array that contains positive integers representing numeric codes into a MATLAB character array.
	X = double(S) converts the string to its equivalent integer numeric codes.
Tips	• To convert between character arrays and cell arrays of strings, use char and cellstr. Most string functions support both types.

•	To determine v	whether S is a	character	array or	cell	array,	call
	<pre>ischar(S) or :</pre>	iscellstr(S)	•				

Examples Create a simple string that includes a single quote.

```
msg = 'You''re right!'
msg =
You're right!
```

Create the string name using two methods of concatenation.

```
name = ['Thomas' ' R. ' 'Lee']
name = strcat('Thomas',' R.',' Lee')
```

Create a character array of strings.

```
C = char('Hello','Goodbye','Yes','No')
C =
Hello
Goodbye
Yes
No
```

Create a cell array of strings.

See Also char, isstrprop, cellstr, ischar, isletter, isspace, iscellstr, sprintf, sscanf, text, input

strjust

Purpose	Justify character array
Syntax	T = strjust(S) T = strjust(S, 'right') T = strjust(S, 'left') T = strjust(S, 'center')
Description	T = strjust(S) or T = strjust(S, 'right') returns a right-justified version of the character array S.
	T = strjust(S, 'left') returns a left-justified version of S.
	T = strjust(S, 'center') returns a center-justified version of S.
See Also	deblank, strtrim

Purpose	Find possible matches for string		
Syntax	x = strmatch(str, strarray) x = strmatch(str, strarray, 'exact')		
Description	<pre>x = strmatch(str, strarray) looks through the rows of the character array or cell array of strings strarray to find strings that begin with the text contained in str, and returns the matching row indices. If strmatch does not find str in strarray, x is an empty matrix ([]). Any trailing space characters in str or strarray are ignored when matching. strmatch is fastest when strarray is a character array.</pre>		
	 x = strmatch(str, strarray, 'exact') compares str with each row of strarray, looking for an exact match of the entire strings. Any trailing space characters in str or strarray are ignored when matching. 		
Examples	The statement		
	<pre>x = strmatch('max', char('max', 'minimax', 'maximum'))</pre>		
	returns $x = [1; 3]$ since rows 1 and 3 begin with 'max'. The statement		
	<pre>x = strmatch('max', char('max', 'minimax', 'maximum'),'exact')</pre>		
	returns $x = 1$, since only row 1 matches 'max' exactly.		
See Also	strcmp, strcmpi, strncmp, strncmpi, strfind, regexp, regexpi, regexprep		

strncmp, strncmpi

Purpose	Compare first n characters of strings		
Syntax	<pre>TF = strncmp('str1', 'str2', n) TF = strncmp('str', C, n) TF = strncmp(C1, C2, n)</pre>		
	Each of these syntaxes applies to both strncmp and strncmpi. The strncmp function is case sensitive in matching strings, while strncmpi is not.		
Description	Although the following descriptions show only strncmp, they apply to strncmpi as well. The two functions are the same except that strncmpi compares strings without sensitivity to letter case:		
	TF = strncmp('str1', 'str2', n) compares the first n characters of strings str1 and str2 and returns logical 1 (true) if they are identical, and returns logical 0 (false) otherwise. str1 and str2 can be character arrays of any dimension.		
	TF = strncmp('str', C, n) compares the first n characters of str to the first n characters of each element of cell array C, where str is a character vector (or a 1-by-1 cell array), and C is a cell array of strings. The function returns TF, a logical array that is the same size as C and contains logical 1 (true) for those elements of C that are a match, and logical 0 (false) for those elements that are not. The order of the first two input arguments is not important.		
	TF = strncmp(C1, C2, n) compares each element of C1 to the same element in C2, where C1 and C2 are equal-size cell arrays of strings. Input C1 or C2 can also be a character array with the right number of rows. The function attempts to match only the first n characters of each string. The function returns TF, a logical array that is the same size as C1 and C2, and contains logical 1 (true) for those elements of C1 and C2 that are a match, and logical 0 (false) for those elements that are not.		
Remarks	These functions are intended for comparison of character data. When used to compare numeric data, they return logical 0.		

Any leading and trailing blanks in either of the strings are explicitly included in the comparison.

The value returned by strncmp and strncmpi is not the same as the C language convention.

strncmp and strncmpi support international character sets.

Examples Example 1

From a list of 10 MATLAB functions, find those that apply to using a camera:

```
function_list = {'calendar' 'case' 'camdolly' 'circshift' ...
                 'caxis' 'camtarget' 'cast' 'camorbit' ...
                 'callib' 'cart2sph'};
strncmp(function_list, 'cam', 3)
ans =
              1
                           1
    0
         0
                  0
                        0
                                  0
                                      1
                                            0
                                                 0
function_list{strncmp(function_list, 'cam', 3)}
ans =
  camdolly
ans =
  camtarget
ans =
  camorbit
```

Example 2

Create two 5-by-10 string arrays str1 and str2 that are equal except for the element at row 4, column 3. Using linear indexing, this is element 14:

CCCCCCCCC DDDDDDDDD EEEEEEEEE str2 = str1; str2(4,3) = '-' str2 = AAAAAAAAAA BBBBBBBBB CCCCCCCCC DD-DDDDDD EEEEEEEEE

Because MATLAB compares the arrays in linear order (that is, column by column rather than row by row), strncmp finds only the first 13 elements to be the same:

```
regexptranslate
```

See Also

Purpose Read formatted data from string

Note strread will be removed in a future version. Use textscan instead.

Syntax	<pre>A = strread('str') [A, B,] = strread('str') [A, B,] = strread('str', 'format') [A, B,] = strread('str', 'format', N) [A, B,] = strread('str', 'format', N, param, value,)</pre>
Description	A = strread('str') reads numeric data from input string str into a 1-by-N vector A, where N equals the number of whitespace-separated numbers in str. Use this form only with strings containing numeric data. See "Example 1" on page 2-3743 below.
	[A, B,] = strread('str') reads numeric data from the string input str into scalar output variables A, B, and so on. The number of output variables must equal the number of whitespace-separated numbers in str. Use this form only with strings containing numeric data. See "Example 2" on page 2-3744 below.
	[A, B,] = strread('str', 'format') reads data from str into variables A, B, and so on using the specified format. The number of output variables A, B, etc. must be equal to the number of format specifiers (e.g., %s or %d) in the format argument. You can read all of the data in str to a single output variable as long as you use only one format specifier in the command. See "Example 4" on page 2-3744 and "Example 5" on page 2-3745 below.
	The table Formats for strread on page 2-3740 lists the valid format specifiers. More information on using formats is available under "Formats" on page 2-3743 in the Remarks section below.
	$[A, B, \ldots]$ = strread('str', 'format', N) reads data from str reusing the format string N times, where N is an integer greater than zero. If N is -1, strread reads the entire string. When str contains

only numeric data, you can set format to the empty string (''). See "Example 3" on page 2-3744 below.

[A, B, ...] = strread('str', 'format', N, param, value, ...) customizes strread using param/value pairs, as listed in the table Parameters and Values for strread on page 2-3741 below. When str contains only numeric data, you can set format to the empty string (''). The N argument is optional and may be omitted entirely. See "Example 7" on page 2-3746 below.

Format	Action	Output
Literals (ordinary characters)	Ignore the matching characters. For example, in a string that has Dept followed by a number (for department number), to skip the Dept and read only the number, use 'Dept' in the format string.	None
%d	Read a signed integer value.	Double array
%u	Read an integer value.	Double array
%f	Read a floating-point value.	Double array
°∕sS	Read a white-space separated string.	Cell array of strings
%q	Read a double quoted string, ignoring the quotes.	Cell array of strings
%C	Read characters, including white space.	Character array
%[]	Read the longest string containing characters specified in the brackets.	Cell array of strings

Formats for strread

Formats for strread (Continued)

Format	Action	Output
%[^]	Read the longest nonempty string containing characters that are not specified in the brackets.	Cell array of strings
%*	Ignore the characters following *. See "Example 8" on page 2-3746 below.	No output
%w	Read field width specified by w. The %f format supports %w.pf, where w is the field width and p is the precision.	

Parameters and Values for strread

param	value	Action
whitespace	Any from the list below:\bBackspace\nNew line\rCarriage return\tHorizontal tab\\Backslash%Percent sign''Single quotation mark	Treats vector of characters, *, as white space. Default is \b\r\n\t.
delimiter	Delimiter character	Specifies delimiter character. Default is one or more whitespace characters.
expchars	Exponent characters	Default is eEdD.

param	value	Action
bufsize	Positive integer	Specifies the maximum string length, in bytes. Default is 4095.
commentstyle	matlab	Ignores characters after %.
commentstyle	shell	Ignores characters after #.
commentstyle	с	Ignores characters between /* and */.
commentstyle	C++	Ignores characters after //.
emptyvalue	Value to return for empty numeric fields in delimited files	Default is NaN.

Parameters and Values for strread (Continued)

Remarks

If you terminate the input string with a newline character (\n), strread returns arrays of equal size by padding arrays of lesser size with the emptyvalue character:

If you remove the n from the input string of this example, array A continues to be a 2-by-1 array, but B and C are now 1-by-1.

Delimiters

If your data uses a character other than a space as a delimiter, you must use the strread parameter 'delimiter' to specify the delimiter. For example, if the string str used a semicolon as a delimiter, you would use this command:

```
[names, types, x, y, answer] = strread(str,'%s %s %f ...
%d %s','delimiter',';')
```

Formats

The format string determines the number and types of return arguments. The number of return arguments must match the number of conversion specifiers in the format string.

The strread function continues reading str until the entire string is read. If there are fewer format specifiers than there are entities in str, strread reapplies the format specifiers, starting over at the beginning. See "Example 5" on page 2-3745 below.

The format string supports a subset of the conversion specifiers and conventions of the C language fscanf routine. White-space characters in the format string are ignored.

Preserving White-Space

If you want to preserve leading and trailing spaces in a string, use the whitespace parameter as shown here:

Examples Example 1

Read numeric data into a 1-by-5 vector:

strread

```
a = strread('0.41 8.24 3.57 6.24 9.27')
a =
0.4100 8.2400 3.5700 6.2400 9.2700
```

Example 2

Read numeric data into separate scalar variables:

Example 3

Read the only first three numbers in the string, also formatting as floating point:

Example 4

Truncate the data to one decimal digit by specifying format %3.1f. The second specifier, %*1d, tells strread not to read in the remaining decimal digit:

```
a = strread('0.41 8.24 3.57 6.24 9.27', '%3.1f %*1d')
a =
```

0.4000 8.2000 3.5000 6.2000

9.2000

Example 5

Read six numbers into two variables, reusing the format specifiers:

Example 6

Read string and numeric data to two output variables. Ignore commas in the input string:

```
str = 'Section 4, Page 7, Line 26';
[name value] = strread(str, '%s %d,')
name =
    'Section'
    'Page'
    'Line'
value =
    4
    7
    26
```

Example 7

Read the string used in the last example, but this time delimiting with commas instead of spaces:

Example 8

Read selected portions of the input string:

```
str = '';
[border width space] = strread(str, ...
    '%*s%*s %c %*s "%4s" %*s %c', 'delimiter', '= ')
border =
    5
width =
    '100%'
space =
    0
```

Example 9

Read the string into two vectors, restricting the Answer values to T and F. Also note that two delimiters (comma and space) are used here:

```
'Answer_2:'
'Answer_3:'
b =
'T'
'F'
'F'
```

See Also

textscan, sscanf

strrep

Purpose	Find and replace substring
Syntax	<pre>modifiedStr = strrep(origStr, oldSubstr, newSubstr)</pre>
Description	<pre>modifiedStr = strrep(origStr, oldSubstr, newSubstr) replaces all occurrences of the string oldSubstr within string origStr with the string newSubstr.</pre>
Tips	• strrep accepts input combinations of single strings, strings in scalar cells, same-sized cell arrays of strings, and character arrays with the same number of rows as cell array inputs. If any inputs are cell arrays, strrep returns a cell array.
	• The strrep function does not find empty strings for replacement. That is, when <i>origStr</i> and <i>oldSubstr</i> both contain the empty string (''), strrep does not replace '' with the contents of <i>newSubstr</i> .
	• Before replacing strings, strrep finds all instances of <i>oldSubstr</i> in <i>origStr</i> , like the strfind function. For overlapping patterns, strrep performs multiple replacements. See the final example in the Examples section.
Examples	Replace text in a character array:
	claim = 'This is a good example.'; new_claim = strrep(claim, 'good', 'great')
	MATLAB returns:
	new_claim = This is a great example.
Examples	<pre>(''), strrep does not replace '' with the contents of newSubstr. Before replacing strings, strrep finds all instances of oldSubstr in origStr, like the strfind function. For overlapping patterns, strrep performs multiple replacements. See the final example in the Examples section. Replace text in a character array: claim = 'This is a good example.'; new_claim = strrep(claim, 'good', 'great') MATLAB returns: new_claim =</pre>

Replace text in a cell array:

```
d_files = strrep(c_files, 'c:', 'd:')
```

MATLAB returns:

d_files = 'd:\cookies.m' 'd:\candy.m' 'd:\calories.m'

Replace text in a cell array with values in a second cell array:

missing_info = {'Start: __'; ... 'End: __'}; dates = {'01/01/2001'; ... '12/12/2002'}; complete = strrep(missing_info, '__', dates) MATLAB returns:

complete = 'Start: 01/01/2001' 'End: 12/12/2002'

Compare the use of strrep and regexprep to replace a string with a repeated pattern:

```
repeats = 'abc 2 def 22 ghi 222 jkl 2222';
indices = strfind(repeats, '22')
using_strrep = strrep(repeats, '22', '*')
using_regexprep = regexprep(repeats, '22', '*')
```

MATLAB returns:

See Also strfind | regexprep

Purpose	Selected parts of string
Syntax	token = strtok(str) token = strtok(str, delimiter) [token, remain] = strtok('str',)
Description	token = strtok(str) parses input string str from left to right, returning part or all of that string in token. Using the white-space character as a delimiter, the token output begins at the start of str, skipping any delimiters that might appear at the start, and includes

skipping any delimiters that might appear at the start, and includes all characters up to either the next delimiter or the end of the string. White-space characters include space (ASCII 32), tab (ASCII 9), and carriage return (ASCII 13).

The str argument can be a string of characters enclosed in single quotation marks, a cell array of strings each enclosed in single quotation marks, or a variable representing either of the two. If str is a cell array of N strings, then token is a cell array of N tokens, with token{1} derived from str{1}, token{2} from str{2}, and so on.

token = strtok(str, delimiter) is the same as the above syntax except that you specify the delimiting character(s) yourself using the delimiter character vector input. White-space characters are not considered to be delimiters when using this syntax unless you include them in the delimiter argument. If the delimiter input specifies more than one character, MATLAB treats each character as a separate delimiter; it does not treat the multiple characters as a delimiting string. The number and order of characters in the delimiter argument is unimportant. Do not use escape sequences as delimiters. For example, use char(9) rather than '\t' for tab.

[token, remain] = strtok('str', ...) returns in remain that part of str, if any, that follows token. If no delimiters are found in the body of the input string, then the entire string (excluding any leading delimiting characters) is returned in token, and remain is an empty string (''). If str is a cell array of strings, token is a cell array of tokens and remain is a cell array of string remainders.

Examples

Example 1

This example uses the default white-space delimiter. Note that space characters at the start of the string are not included in the token output, but the space character that follows token is included in remain:

```
s = ' This is a simple example.';
[token, remain] = strtok(s)
token =
This
remain =
is a simple example.
```

Example 2

Take a string of HTML code and break it down into segments delimited by the < and > characters. Write a while loop to parse the string and print each segment:

```
s = sprintf('%s%s%s%s', ...
'', ...
<a name="13474"></a>token = strtok', ...
'(''str'', delimiter)<a name="13475"></a>', ...
'token = strtok(''str'')');
remain = s;
while true
  [str, remain] = strtok(remain, '<>');
  if isempty(str), break; end
  disp(sprintf('%s', str))
end
```

Here is the output:

ul class=continued li class=continued pre

```
a name="13474"
/a
token = strtok('str', delimiter)
a name="13475"
/a
token = strtok('str')
```

Example 3

Using strtok on a cell array of strings returns a cell array of strings in token and a character array in remain:

```
s = { 'all in good time'; ...
        'my dog has fleas'; ...
        'leave no stone unturned'};
  remain = s;
  for k = 1:4
      [token, remain] = strtok(remain);
     token
  end
Here is the output:
  token =
       'all'
       'my'
       'leave'
  token =
       'in'
       'dog'
       'no'
  token =
       'good'
       'has'
       'stone'
  token =
```

strtok

'time' 'fleas' 'unturned'

See Also

strfind, strncmp, strcmp, textscan

Purpose	Remove leading and trailing white space from string	
Syntax	S = strtrim(str) C = strtrim(cstr)	
Description	S = strtrim(str) returns a copy of string str with all leading and trailing white-space characters removed. A white-space character is one for which the isspace function returns logical 1 (true).	
	C = strtrim(cstr) returns a copy of the cell array of strings cstr with all leading and trailing white-space characters removed from each string in the cell array.	
Examples	<pre>Remove the leading white-space characters (spaces and tabs) from str: str = sprintf(' \t Remove leading white-space') str = Remove leading white-space str = strtrim(str) str = Remove leading white-space Remove leading and trailing white-space from the cell array of strings: cstr = {' Trim leading white-space from the cell array of strings: cstr = {' Trim leading white-space '}; 'Trim trailing white-space '}; cstr = strtrim(cstr) cstr = 'Trim leading white-space' 'Trim trailing white-space'</pre>	
See Also	isspace, cellstr, deblank, strjust	

struct

Purpose	Create structure array
Syntax	<pre>s = struct('field1', values1, 'field2', values2,) s = struct('field1', {}, 'field2', {},) s = struct s = struct([]) s = struct(obj)</pre>
Description	<pre>s = struct('field1', values1, 'field2', values2,) creates a structure array with the specified fields and values. Each value input (values1, values2, etc.), can either be a cell array or a scalar value. Those that are cell arrays must all have the same dimensions.</pre>
	The size of the resulting structure is the same size as the value cell arrays, or 1-by-1 if none of the values is a cell array. Elements of the value array inputs are placed into corresponding structure array elements.
	Note If any of the values fields is an empty cell array {}, the MATLAB software creates an empty structure array in which all fields are also empty.
	Structure field names must begin with a letter, and are case-sensitive. The rest of the name may contain letters, numerals, and underscore characters. Use the namelengthmax function to determine the maximum length of a field name.
	<pre>s = struct('field1', {}, 'field2', {},) creates an empty structure with fields field1, field2,</pre>
	s = struct creates a 1-by-1 structure with no fields.
	<pre>s = struct([]) creates an empty structure with no fields.</pre>
	<pre>s = struct(obj) creates a structure s that is identical to the underlying structure in the input object obj. MATLAB does not convert</pre>

obj, but rather creates s as a new structure. This structure does not retain the class information in obj.

Remarks Two Ways to Access Fields

The most common way to access the data in a structure is by specifying the name of the field that you want to reference. Another means of accessing structure data is to use dynamic field names. These names express the field as a variable expression that MATLAB evaluates at run-time.

Fields That Are Cell Arrays

To create fields that contain cell arrays, place the cell arrays within a value cell array. For instance, to create a 1-by-1 structure, type

```
s = struct('strings',{{'hello','yes'}},'lengths',[5 3])
s =
strings: {'hello' 'yes'}
lengths: [5 3]
```

Specifying Cell Versus Noncell Values

When using the syntax

```
s = struct('field1', values1, 'field2', values2, ...)
```

the values inputs can be cell arrays or scalar values. For those values that are specified as a cell array, MATLAB assigns each element of values{ m,n,\ldots } to the corresponding field in each element of structure s:

```
s(m,n,...).fieldN = valuesN{m,n,...}
```

For those values that are scalar, MATLAB assigns that single value to the corresponding field for all elements of structure **s**:

s(m,n,...).fieldN = valuesN

See Example 3, below.

Examples

Example 1

The command

```
s = struct('type', {'big','little'}, 'color', {'red'}, ...
'x', {3 4})
```

produces a structure array s:

```
s =
1x2 struct array with fields:
    type
    color
    x
```

The value arrays have been distributed among the fields of **s**:

```
s(1)
ans =
    type: 'big'
    color: 'red'
        x: 3
s(2)
ans =
        type: 'little'
        color: 'red'
        x: 4
```

Example 2

Similarly, the command

a.b = struct('z', {});

produces an empty structure a.b with field z.

```
a.b
ans =
0x0 struct array with fields:
z
```

Example 3

This example initializes one field f1 using a cell array, and the other f2 using a scalar value:

```
s = struct('f1', {1 3; 2 4}, 'f2', 25)
s =
2x2 struct array with fields:
    f1
    f2
```

Field f1 in each element of s is assigned the corresponding value from the cell array $\{1 \ 3; \ 2 \ 4\}$:

```
s.f1
ans =
1
ans =
2
ans =
3
ans =
4
```

Field f2 for all elements of s is assigned one common value because the <code>values</code> input for this field was specified as a scalar:

```
s.f2
ans =
25
ans =
25
ans =
25
ans =
25
```

See Also	isstruct fieldnames isfield orderfields getfield setfield rmfield substruct deal cell2struct struct2cell namelengthmax
How To	"Creating a Structure"
	 "Creating Field Names Dynamically"
	 "Returning Data from a Struct Array"

Purpose	Convert structure to cell array
Syntax	
Symux	c = struct2cell(s)
Description	c = struct2cell(s) converts the m-by-n structure s (with p fields) into a p-by-m-by-n cell array c.
	If structure s is multidimensional, cell array c has size [p size(s)].
Examples	The commands
	clear s, s.category = 'tree'; s.height = 37.4; s.name = 'birch';
	create the structure
	s =
	category: 'tree'
	height: 37.4000
	name: 'birch'
	Converting the structure to a cell array,
	c = struct2cell(s)
	c =
	'tree'
	[37.4000]
	'birch'
See Also	cell2struct, cell, iscell, struct, isstruct, fieldnames, dynamic

field names

structfun

Purpose	Apply function to each field of scalar structure
Syntax	A = structfun(fun, S) [A, B,] = structfun(fun, S) [A,] = structfun(fun, S, 'param1', value1,)
Description	A = structfun(fun, S) applies the function specified by fun to each field of scalar structure S, and returns the results in array A. fun is a function handle to a function that takes one input argument and returns a scalar value. Return value A is a column vector that has one element for each field in input structure S. The Nth element of A is the result of applying fun to the Nth field of S, and the order of the fields is the same as that returned by a call to fieldnames. (A is returned as one or more scalar structures when the UniformOutput option is set to false. See the table below.))
	fun must return values of the same class each time it is called. If fun is a handle to an overloaded function, then structfun follows MATLAB dispatching rules in calling the function.
	[A, B,] = structfun(fun, S) returns arrays A, B,, each array corresponding to one of the output arguments of fun. structfun calls fun each time with as many outputs as there are in the call to structfun. fun can return output arguments having different classes, but the class of each output must be the same each time fun is called.
	<pre>[A,] = structfun(fun, S, 'param1', value1,) enables you to specify optional parameter name/parameter value pairs. Parameters are</pre>

Parameter	Value
'UniformOutput'	Logical value indicating whether or not the outputs of fun can be returned without encapsulation in a structure. The default value is true.
	If equal to logical 1 (true), fun must return scalar values that can be concatenated into an array. The outputs can be any of the following types: numeric, logical, char, struct, or cell.
	If equal to logical 0 (false), structfun returns a scalar structure or multiple scalar structures having fields that are the same as the fields of the input structure S. The values in the output structure fields are the results of calling fun on the corresponding values in the input structure B. In this case, the outputs can be of any data type.
'ErrorHandler'	Function handle specifying the function MATLAB is to call if the call to fun fails. MATLAB calls the error handling function with the following input arguments:
	• A structure, with the fields 'identifier', 'message', and 'index', respectively containing the identifier of the error that occurred, the text of the error message, and the number of the field (in the same order as returned by field names) at which the error occurred.
	• The input argument at which the call to the function failed.
	The error handling function should either rethrow an error or return the same number of outputs as fun. These outputs are then returned as the outputs of structfun. If

structfun

Parameter	Value
	'UniformOutput' is true, the outputs of the error handler must also be scalars of the same type as the outputs of fun.
	<pre>For example, function [A, B] = errorFunc(S, varargin) warning(S.identifier, S.message); A = NaN; B = NaN;</pre>
	If an error handler is not specified, the error from the call to fun is rethrown.

Examples To create shortened weekday names from the full names, for example: Create a structure with strings in several fields:

s.f1 =	'Sunday';
s.f2 =	'Monday';
s.f3 =	'Tuesday';
s.f4 =	'Wednesday';
s.f5 =	'Thursday';
s.f6 =	'Friday';
s.f7 =	'Saturday';
shortNa	nmes = structfun(@(x) (x(1:3)), s, 'UniformOutput', false);

See Also cellfun, arrayfun, function_handle, cell2mat, spfun

Purpose	Concatenate strings vertically	
	Note strvcat will be removed in a fur Unlike strvcat, the char function does	
Syntax	S = strvcat(t1, t2, t3,) S = strvcat(c)	
Description	<pre>S = strvcat(t1, t2, t3,) forms the character array S containing the text strings (or string matrices) t1,t2,t3, as rows. Spaces are appended to each string as necessary to form a valid matrix. Empty arguments are ignored.</pre>	
	<pre>S = strvcat(c) when c is a cell array of c as an input to strvcat. Empty stri </pre>	
Remarks	If each text parameter, ti, is itself a ch them vertically to create arbitrarily lar	
Examples	The command strvcat('Hello','Yes') is the same as ['Hello';'Yes '], except that strvcat performs the padding automatically.	
	t1 = 'first'; t2 = 'string'; t	3 = 'matrix'; t4 = 'second';
	S1 = strvcat(t1, t2, t3)	S2 = strvcat(t4, t2, t3)
	S1 =	S2 =
	first string	second string
	matrix	matrix
	S3 = strvcat(S1, S2)	
	S3 =	

strvcat

first string matrix second string matrix

See Also strcat, cat, vertcat, horzcat, int2str, mat2str, num2str, strings, special character []

Purpose	Convert subscripts to linear indices	
Syntax	<pre>linearInd = sub2ind(matrixSize, rowSub, colSub) linearInd = sub2ind(arraySize, dim1Sub, dim2Sub, dim3Sub,</pre>	
Description	<pre>linearInd = sub2ind(matrixSize, rowSub, colSub) returns the linear index equivalents to the row and column subscripts rowSub and colSub for a matrix of size matrixSize. The matrixSize input is a 2-element vector that specifies the number of rows and columns in the matrix as [nRows, nCols]. The rowSub and colSub inputs are positive, whole number scalars or vectors that specify one or more row-column subscript pairs for the matrix. Example 3 demonstrates the use of vectors for the rowSub and colSub inputs.</pre>	
	<pre>linearInd = sub2ind(arraySize, dim1Sub, dim2Sub, dim3Sub,) returns the linear index equivalents to the specified subscripts for each dimension of an N-dimensional array of size arraySize. The arraySize input is an n-element vector that specifies the number of dimensions in the array. The dimNSub inputs are positive, whole number scalars or vectors that specify one or more row-column subscripts for the matrix.</pre>	
	The <i>rowSub</i> and <i>co1Sub</i> inputs must belong to the same class. The <i>linearInd</i> output is the same class as the subscript inputs.	
	If needed, sub2ind assumes that unspecified trailing subscripts are 1. See Example 2, below.	
Examples	<pre>Example 1 This example converts the subscripts (2, 1, 2) for three-dimensional array A to a single linear index. Start by creating a 3-by-4-by-2 array A: rand('state', 0); % Initialize random number generator. A = rand(3, 4, 2) A(:,:,1) = 0.9501 0.4860 0.4565 0.4447</pre>	

0.2311	0.8913	0.0185	0.6154
0.6068	0.7621	0.8214	0.7919
A(:,:,2) =			
0.9218	0.4057	0.4103	0.3529
0.7382	0.9355	0.8936	0.8132
0.1763	0.9169	0.0579	0.0099

Find the linear index corresponding to (2, 1, 2):

linearInd = sub2ind(size(A), 2, 1, 2)
linearInd =
 14

Make sure that these agree:

A(2, 1, 2)	A(14)
ans =	and =
0.7382	0.7382

Example 2

Using the 3-dimensional array A defined in the previous example, specify only 2 of the 3 subscript arguments in the call to sub2ind. The third subscript argument defaults to 1.

The command

```
linearInd = sub2ind(size(A), 2, 4)
ans =
    11
```

is the same as

Example 3

Using the same 3-dimensional input array A as in Example 1, accomplish the work of five separate sub2ind commands with just one.

Replace the following commands:

sub2ind(size(A), 3, 3, 2); sub2ind(size(A), 2, 4, 1); sub2ind(size(A), 3, 1, 2); sub2ind(size(A), 1, 3, 2); sub2ind(size(A), 2, 4, 1);

with a single command:

Verify that these linear indices access the same array elements as their subscripted counterparts:

 $\begin{bmatrix} A(3,3,2), & A(2,4,1), & A(3,1,2), & A(1,3,2), & A(2,4,1) \end{bmatrix}$ ans = 0.0579 0.6154 0.1763 0.4103 0.6154 A([21, 11, 15, 19, 11])ans = 0.0579 0.6154 0.1763 0.4103 0.6154

See Also ind2sub | find | size

subplot

Purpose Create axes in tiled positions

1			1		
0.5		0.3	5		
0		_	ں لے		-
Ū.	0.5	1	ļΟ.	0.5	1
1			1		
0.5		0.	5		
nL		_	nL		_
Ŭ	0.5	1	Ŭ0	0.5	1

GUI Alternatives

To add subplots to a figure, click one of the *New Subplot* icons in the Figure Palette, and slide right to select an arrangement of subplots. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation.

Syntax h = subplot(m,n,p) or subplot(mnp)
subplot(m,n,p,'replace')
subplot(m,n,P)
subplot(h)
subplot('Position',[left bottom width height])
subplot(..., prop1, value1, prop2, value2, ...)
h = subplot(...)

Description subplot divides the current figure into rectangular panes that are numbered rowwise. Each pane contains an axes object which you can manipulate using Axes Properties. Subsequent plots are output to the current pane.

h = subplot(m,n,p) or subplot(mnp) breaks the figure window into an m-by-n matrix of small axes, selects the pth axes object for the current plot, and returns the axes handle. The axes are counted along the top row of the figure window, then the second row, etc. For example,

subplot(2,1,1), plot(income)
subplot(2,1,2), plot(outgo)

plots income on the top half of the window and outgo on the bottom half. If the CurrentAxes is nested in a uipanel, the panel is used as the parent for the subplot instead of the current figure. The new axes object becomes the current axes.

subplot(m,n,p, 'replace') If the specified axes object already exists, delete it and create a new axes.

subplot(m,n,P), where P is a vector, specifies an axes position that covers all the subplot positions listed in P, including those spanned by P. For example, subplot(2,3,[2 5]) creates one axes spanning positions 2 and 5 only (because there are no intervening locations in the grid), while subplot(2,3,[2 6]) creates one axes spanning positions 2, 3, 5, and 6.

subplot(h) makes the axes object with handle h current for subsequent plotting commands.

subplot('Position',[left bottom width height]) creates an axes at the position specified by a four-element vector. left, bottom, width, and height are in normalized coordinates in the range from 0.0 to 1.0.

subplot(..., prop1, value1, prop2, value2, ...) sets the specified property-value pairs on the subplot axes object. Available property/value pairs are described more fully in Axes Properties. To add the subplot to a specific figure or uipanel, pass the handle as the value for the Parent property. You cannot specify both a Parent and a Position; that is, subplot('Position',[left bottom width height], 'Parent',h) is not a valid syntax.

h = subplot(...) returns the handle to the new axes object.

Remarks

If a subplot specification causes a new axis to overlap a existing axis, the existing axis is deleted - unless the position of the new and existing axis are identical. For example, the statement subplot(1,2,1) deletes all existing axes overlapping the left side of the figure window and creates a new axis on that side—unless there is an axes there with a position that exactly matches the position of the new axes (and 'replace' was not specified), in which case all other overlapping axes will be deleted and the matching axes will become the current axes.

You can add subplots to GUIs as well as to figures. For information about creating subplots in a GUIDE-generated GUI, see "Creating Subplots" in the MATLAB Creating Graphical User Interfaces documentation.

If a subplot specification causes a new axes object to overlap any existing axes, subplot deletes the existing axes object and uicontrol objects. However, if the subplot specification exactly matches the position of an existing axes object, the matching axes object is not deleted and it becomes the current axes.

subplot(1,1,1) or clf deletes all axes objects and returns to the
default subplot(1,1,1) configuration.

You can omit the parentheses and specify subplot as

subplot mnp

where m refers to the row, n refers to the column, and p specifies the pane.

Be aware when creating subplots from scripts that the Position property of subplots is not finalized until either

- A drawnow command is issued.
- MATLAB returns to await a user command.

That is, the value obtained for subplot i by the command

get(h(i), 'position')

will not be correct until the script refreshes the plot or exits.


Special Case: subplot(111)

The command subplot(111) is not identical in behavior to subplot(1,1,1) and exists only for compatibility with previous releases. This syntax does not immediately create an axes object, but instead sets up the figure so that the next graphics command executes a clf reset (deleting all figure children) and creates a new axes object in the default position. This syntax does not return a handle, so it is an error to specify a return argument. (MATLAB implements this behavior by setting the figure's NextPlot property to replace.)

Examples Upper and Lower Subplots with Titles

To plot income in the top half of a figure and outgo in the bottom half,


```
income = [3.2 4.1 5.0 5.6];
outgo = [2.5 4.0 3.35 4.9];
subplot(2,1,1); plot(income)
title('Income')
subplot(2,1,2); plot(outgo)
title('Outgo')
```



Subplots in Quadrants

The following illustration shows four subplot regions and indicates the command used to create each.

subplot




Asymmetrical Subplots

The following combinations produce asymmetrical arrangements of subplots.


subplot(2,2,[1 3])

subplot(2,2,2)
subplot(2,2,4)



You can also use the colon operator to specify multiple locations if they are in sequence.

subplot(2,2,1:2)
subplot(2,2,3)
subplot(2,2,4)



Suppressing Axis Ticks

When you create many subplots in a figure, the axes tickmarks, which are shown by default, can either be obliterated or can cause axes to collapse, as the following code demonstrates:


```
figure
for i=1:12
    subplot(12,1,i)
    plot (sin(1:100)*10^(i-1))
end
```

// Figure 1 File Edit Vi	ew	Insert	Tools D)esktop	Window	Help					
🗅 🚅 日		ß	Q Q								
l)	10	20	30	40	50	60	70	80	90	
Ċ)	10	20	30	40	50	60	70	80	90	
Ċ)	10	20	30	40	50	60	70	80	90	
Ċ)	10	20	30	40	50	60	70	80	90	
l C)	10	20	30	40	50	60	70	80	90	
l C)	10	20	30	40	50	60	70	80	90	
Ċ)	10	20	30	40	50	60	70	80	90	
Ċ)	10	20	30	40	50	60	70	80	90	
C)	10	20	30	40	50	60	70	80	90	
ł)	10	20	30	40	50	60	70	80	90	
()	10	20	30	40	50	60	70	80	90	
l ()	10	20	30	40	50	60	70	80	90	

One way to get around this issue is to enlarge the figure to create enough space to properly display the tick labels.


Another approach is to eliminate the clutter by suppressing xticks and yticks for subplots as data are plotted into them. You can then label a single axes if the subplots are stacked, as follows:

```
figure
for i=1:12
    subplot(12,1,i)
    plot (sin(1:100)*10^(i-1))
    set(gca,'xtick',[],'ytick',[])
end
% Reset the bottom subplot to have xticks
set(gca,'xtickMode', 'auto')
```



Plotting Axes Over Subplots

Place a plot in the center, on top of four other plots, using the **axes** and **subplot** functions:



See Also

axes, cla, clf, figure, gca

"Basic Plots and Graphs" on page 1-96 for more information

"Creating Subplots" in the MATLAB Creating Graphical User Interfaces documentation describes adding subplots to GUIs.

Purpose	Subscripted assignment	
Syntax	A = subsasgn(A, S, B)	
Description	A = subsasgn(A, S, B) is called by MATLAB for the syntax $A(i) = B, A\{i\} = B, or A.i = B$ when A is an object.	
	MATLAB uses the built-in subsasgn function to interpret indexed assignment statements. Modify the indexed assignment behavior of classes by overloading subsasgn in the class.	
	If A is a fundamental class (see "Classes (Data Types)"), then an indexed reference to A calls the built-in subsasgn function. It does not call a subsasgn method that you have overloaded for that class. Therefore, if A is an array of class double, and there is an @double/subsasgn method on your MATLAB path, the statement A(I) = B calls the MATLAB built-in subsasgn function.	
Input Arguments	A Object S	
	struct array with two fields, type and subs.	
	• type is a string containing '()', '{}', or '.', where '()' specifies integer subscripts, '{}' specifies cell array subscripts, and '.' specifies subscripted structure fields.	
	• subs is a cell array or string containing the actual subscripts.	
	В	
	Assignment value (right-hand side)	
Output Arguments	A Result of evaluating assignment.	

subsasgn

Examples	See how MATLAB calls subsasgn for the expression:
	A(1:2,:) = B;
	The syntax A(1:2,:) = B calls A = subsasgn(A,S,B) where S is a 1-by-1 structure with S.type = '()' and S.subs = {1:2,':'}. The string ':' indicates a colon used as a subscript.
	See how MATLAB calls subsasgn for the expression:
	A{1:2} = B;
	The syntax A{1:2} = B calls A = subsasgn(A,S,B) where S.type = $\{\}$ and S.subs = {[1 2]}.
	See how MATLAB calls subsasgn for the expression:
	A.field = B;
	The syntax A.field = B calls A = subsasgn(A,S,B) where S.type = '.' and S.subs = 'field'.
	See how MATLAB calls subsasgn for the expression:
	A(1,2).name(3:5)=B;

Simple calls combine in a straightforward way for more complicated indexing expressions. In such cases, length(S) is the number of subscripting levels. For instance, A(1,2).name(3:5)=B calls A=subsasgn(A,S,B) where S is a 3-by-1 structure array with the following values:

```
S(1).type = '()' S(2).type = '.' S(3).type = '()'
S(1).subs = {1,2} S(2).subs = 'name' S(3).subs = {[3 4
5]}
```

Algorithm	In the assignment $A(J,K,) = B(M,N,)$, subscripts J, K, M, N, and so on, can be scalar, vector, or arrays, when all the following are true:
	• The number of subscripts specified for B, excluding trailing subscripts equal to 1, does not exceed the value returned by ndims(B).
	• The number of nonscalar subscripts specified for A equals the number of nonscalar subscripts specified for B. For example, $A(5,1:4,1,2) = B(5:8)$ is valid because both sides of the equation use one nonscalar subscript.
	 The order and length of all nonscalar subscripts specified for A matches the order and length of nonscalar subscripts specified for B. For example, A(1:4, 3, 3:9) = B(5:8, 1:7) is valid because both sides of the equation (ignoring the one scalar subscript 3) use a 4-element subscript followed by a 7-element subscript.
	See numel for information concerning the use of numel with regards to the overloaded subsasgn function.
See Also	subsref substruct
Tutorials	"Indexed Reference and Assignment"

subsindex

Purpose	Subscript indexing with object
Syntax	<pre>ind = subsindex(A)</pre>
Description	<pre>ind = subsindex(A) called by MATLAB for the expression X(A) when A is an object, unless such an expression results in a call to an overloaded subsref or subsasgn method for X. subsindex must return the value of the object as a zero-based integer index. (ind must contain integer values in the range 0 to prod(size(X))-1.) Call subsindex directly from an overloaded subsref or subsasgn method.</pre>
	MATLAB invokes subsindex separately on all the subscripts in an expression, such as $X(A,B)$.
See Also	subsasgn subsasgn
Tutorials	• "Using Objects as Indices"

Purpose	Angle between two subspaces
Syntax	theta = subspace(A,B)
Description	theta = subspace(A,B) finds the angle between two subspaces specified by the columns of A and B. If A and B are column vectors of unit length, this is the same as acos(A'*B).
Remarks	If the angle between the two subspaces is small, the two spaces are nearly linearly dependent. In a physical experiment described by some observations A, and a second realization of the experiment described by B, subspace(A,B) gives a measure of the amount of new information afforded by the second experiment not associated with statistical errors of fluctuations.
Examples	<pre>Consider two subspaces of a Hadamard matrix, whose columns are orthogonal. H = hadamard(8); A = H(:,2:4); B = H(:,5:8); Note that matrices A and B are different sizes — A has three columns and B four. It is not necessary that two subspaces be the same size in order to find the angle between them. Geometrically, this is the angle between two hyperplanes embedded in a higher dimensional space. theta = subspace(A,B) theta = 1.5708 That A and B are orthogonal is shown by the fact that theta is equal to $\pi/2$. theta - pi/2 ans = 0</pre>

subsref

Purpose	Redefine subscripted reference for objects
Syntax	<pre>B = subsref(A,S)</pre>
Description	B = subsref(A,S) is called by MATLAB for the syntax A(i), A{i}, or A.i when A is an object. S is a struct array with two fields, type and subs.
	The type field is string containing '()', '{}', or '.', where '()' specifies integer subscripts, '{}' specifies cell array subscripts, and '.' specifies subscripted structure fields. The subs field is a cell array or a string containing the actual subscripts.
	B is the result of the indexed expression.
	MATLAB uses the built-in subsref function to interpret indexed references to objects. To modify the indexed reference behavior of objects, overload subsref in the class.
	If A is a fundamental class (see "Classes (Data Types)"), then an indexed reference to A calls the built-in subsref function. It does not call a subsref method that you have overloaded for that class. Therefore, if A is an array of class double, and there is an @double/subsref method on your MATLAB path, the statement A(I) calls the MATLAB built-in subsref function.
Examples	See how MATLAB calls subsref for the expression:
	A(1:2,:)
	The syntax A(1:2,:) calls B = subsref(A,S) where S is a 1-by-1 structure with S.type='()' and S.subs={1:2,':'}. The string ':' indicates a colon used as a subscript.
	See how MATLAB calls subsref for the expression: A{1:2}

The syntax A{1:2} calls B = subsref(A,S) where S.type='{}' and S.subs={[1 2]}.

See how MATLAB calls subsref for the expression:

A.field

The syntax A.field calls B = subsref(A,S) where S.type='.' and S.subs='field'.

See how MATLAB calls subsref for the expression:

A(1,2).name(3:5)

Simple calls combine in a straightforward way for more complicated indexing expressions. In such cases, length(S) is the number of subscript levels. For instance, A(1,2).name(3:5) calls subsref(A,S) where S is a 3-by-1 structure array with the following values:

S(1).type='()'	S(2).type='.'	S(3).type='()'
S(1).subs={1,2}	S(2).subs='name'	S(3).subs={[3 4 5]}

See Also numel | subsasgn | substruct

Tutorials • "Indexed Reference and Assignment"

substruct

Purpose	Create structure argument for subsasgn or subsref
Syntax	S = substruct(type1, subs1, type2, subs2,)
Description	<pre>S = substruct(type1, subs1, type2, subs2,) creates a structure with the fields required by an overloaded subsref or subsasgn method. Each type string must be one of '.', '()', or '{}'. The corresponding subs argument must be either a field name (for the '.' type) or a cell array containing the index vectors (for the '()' or '{}' types).</pre>
Output	S
Arguments	struct with these fields:
	• type: one of '.', '()', or '{}'
	• subs: subscript values (field name or cell array of index vectors)
Examples	Call subsref with arguments equivalent to the syntax:
	B = A(3,5).field;
	where A is an object of a class that implements a subsref method
	Use substruct to form the input struct, S:
	<pre>S = substruct('()',{3,5},'.','field');</pre>
	Call the class method:
	<pre>B = subsref(A,S);</pre>
	The struct created by substruct in this example contains:
	S(1)
	ans =


```
type: '()'
subs: {[3] [5]}
S(2)
ans =
type: '.'
subs: 'field'
See Also subsasgn | subsref
Tutorials · "Indexed Reference and Assignment"
```

subvolume

Purpose	Extract subset of volume data set
Syntax	<pre>[Nx,Ny,Nz,Nv] = subvolume(X,Y,Z,V,limits) [Nx,Ny,Nz,Nv] = subvolume(V,limits) Nv = subvolume()</pre>
Description	<pre>[Nx,Ny,Nz,Nv] = subvolume(X,Y,Z,V,limits) extracts a subset of the volume data set V using the specified axis-aligned limits. limits = [xmin,xmax,ymin, ymax,zmin,zmax] (Any NaNs in the limits indicate that the volume should not be cropped along that axis.)</pre>
	The arrays X, Y, and Z define the coordinates for the volume V. The subvolume is returned in NV and the coordinates of the subvolume are given in NX, NY, and NZ.
	[Nx,Ny,Nz,Nv] = subvolume(V,limits) assumes the arrays X, Y, and Z are defined as
	[X,Y,Z] = meshgrid(1:N,1:M,1:P)
	where [M,N,P] = size(V).
	Nv = subvolume() returns only the subvolume.
Examples	This example uses a data set that is a collection of MRI slices of a human skull. The data is processed in a variety of ways:
	• The 4-D array is squeezed (squeeze) into three dimensions and then a subset of the data is extracted (subvolume).
	• The outline of the skull is an isosurface generated as a patch (p1) whose vertex normals are recalculated to improve the appearance when lighting is applied (patch, isosurface, isonormals).
	• A second patch (p2) with interpolated face color draws the end caps (FaceColor, isocaps).
	• The view of the object is set (view, axis, daspect).

- A 100-element grayscale colormap provides coloring for the end caps (colormap).
- Adding lights to the right and left of the camera illuminates the object (camlight, lighting).

subvolume



See Also isocaps, isonormals, isosurface, reducepatch, reducevolume, smooth3

"Volume Visualization" on page 1-111 for related functions

Purpose	Sum of array elements
Syntax	<pre>B = sum(A) B = sum(A,dim) B = sum(, 'double') B = sum(, dim,'double') B = sum(, 'native') B = sum(, dim,'native')</pre>
Description	B = sum(A) returns sums along different dimensions of an array. If A is a vector, $sum(A)$ returns the sum of the elements.
	If A is a matrix, sum(A) treats the columns of A as vectors, returning a row vector of the sums of each column.
	If A is a multidimensional array, sum(A) treats the values along the first non-singleton dimension as vectors, returning an array of row vectors.
	 B = sum(A,dim) sums along the dimension of A specified by scalar dim. The dim input is an integer value from 1 to N, where N is the number of dimensions in A. Set dim to 1 to compute the sum of each column, 2 to sum rows, etc.
	B = sum(, 'double') and B = sum(, dim, 'double') performs additions in double-precision and return an answer of type double, even if A has data type single or an integer data type. This is the default for integer data types.
	B = sum(, 'native') and $B = sum(, dim, 'native')$ performs additions in the native data type of A and return an answer of the same data type. This is the default for single and double.
Remarks	sum(diag(X)) is the trace of X.
Examples	The magic square of order 3 is M = magic(3) M =

8	1	6
3	5	7
4	9	2

This is called a magic square because the sums of the elements in each column are the same.

sum(M) = 15 15 15

as are the sums of the elements in each row, obtained either by transposing or using thedim argument.

• Transposing

```
sum(M') =
15 15 15
```

• Using the dim argument

sum(M,1) ans = 15 15

Nondouble Data Type Support

This section describes the support of sum for data types other than double.

15

Data Type single

You can apply sum to an array of type single and MATLAB software returns an answer of type single. For example,

class(ans) ans = single

Integer Data Types

When you apply sum to any of the following integer data types, MATLAB software returns an answer of type double:

- int8 and uint8
- int16 and uint16
- int32 and uint32

For example,

```
sum(single([2 5 8]));
class(ans)
ans =
single
```

If you want MATLAB to perform additions on an integer data type in the same integer type as the input, use the syntax

```
sum(int8([2 5 8]), 'native');
class(ans)
ans =
int8
```

See Also accumarray, cumsum, diff, isfloat, prod

<u>sum (timeseries)</u>

Purpose	Sum of timeseries data
Syntax	ts_sm = sum(ts) ts_sm = sum(ts,'PropertyName1',PropertyValue1,)
Description	<pre>ts_sm = sum(ts) returns the sum of the time-series data. When ts.Data is a vector, ts_sm is the sum of ts.Data values. When ts.Data is a matrix, ts_sm is a row vector containing the sum of each column of ts.Data (when IsTimeFirst is true and the first dimension of ts is aligned with time). For the N-dimensional ts.Data array, sum always operates along the first nonsingleton dimension of ts.Data.</pre>
	<pre>ts_sm = sum(ts, 'PropertyName1', PropertyValue1,) specifies the following optional input arguments:</pre>
	 'MissingData' property has two possible values, 'remove' (default) or 'interpolate', indicating how to treat missing data during the calculation.
	• 'Quality' values are specified by a vector of integers, indicating which quality codes represent missing samples (for vector data) or missing observations (for data arrays with two or more dimensions).
	 'Weighting' property has two possible values, 'none' (default) or 'time'. When you specify 'time', larger time values correspond to larger weights.
Examples	1 Load a 24-by-3 data array.
	load count.dat
	2 Create a timeseries object with 24 time values.
	<pre>count_ts = timeseries(count,1:24,'Name','CountPerSecond')</pre>
	3 Calculate the sum of each data column for this timeseries object.
	<pre>sum(count_ts)</pre>

	ans =				
		768	1117	1574	
	The sum is ca timeseries o	-	pendently for	each data column in the	
See Also		,, , , , , , , , , , , , , , , , , , , ,	timeseries), eries), times	median (timeseries), series	std

superclasses

Purpose	Superclass names
Syntax	<pre>superclasses('ClassName') superclasses(obj) s = superclasses()</pre>
Description	<pre>superclasses('ClassName') displays the names of all visible superclasses of the MATLAB class with the name ClassName. Visible classes have a Hidden attribute value of false (the default).</pre>
	<pre>superclasses(obj) obj is an instance of a MATLAB class. obj can be either a scalar object or an array of objects.</pre>
	<pre>s = superclasses() returns the superclass names in a cell array of strings.</pre>
Examples	Get the name of the hgsetget class superclass:
	<pre>superclasses('hgsetget')</pre>
	Superclasses for class hgsetget:
	handle
See Also	properties methods events classdef
Tutorials	• "Hierarchies of Classes — Concepts"

Purpose	Establish superior class relationship
Syntax	<pre>superiorto('class1', 'class2',)</pre>
Description	<pre>superiorto('class1', 'class2',) establishes that the class invoking this function in its constructor has higher precedence than the classes in the argument list.</pre>
	The superiorto function establishes a precedence that determines which object method MATLAB calls. Use this function only from a constructor that calls the class function to create an object. For classes defined with classdef statements, see "Specifying Class Precedence".
Examples	Show function dispatching:
	a is an object of class class_a, b is an object of class class_b, and c is an object of class class_c. The constructor method for class_c contains the statement superiorto('class_a'). Then, either of the following two statements:
	e = fun(a,c); e = fun(c,a);
	invokes class_c/fun.
	If you call a function with two objects having an unspecified relationship, MATLAB considers the two objects to have equal precedence. In this case, MATLAB calls the left-most object method. So fun(b,c) calls class_b/fun, while fun(c,b) calls class_c/fun.
See Also	inferiorto

support

Purpose	Open MathWorks Technical Support Web page
Syntax	support
Description	<pre>support opens the MathWorks Technical Support Web page, http://www.mathworks.com/support, in the MATLAB Web browser. This Web page contains resources including</pre>
	• A search engine, including an option for solutions to common problems
	• Information about installation and licensing
	• A patch archive for bug fixes you can download
	• Other useful resources
See Also	doc, web

Purpose

3-D shaded surface plot





GUI Alternatives	To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.
Syntax	<pre>surf(Z) surf(Z,C) surf(X,Y,Z) surf(X,Y,Z,C) surf(,'PropertyName',PropertyValue) surf(axes_handles,) surfc() h = surf()</pre>
Description	Use surf and surfc to view mathematical functions over a rectangular region. surf and surfc create colored parametric surfaces specified by X, Y, and Z, with color specified by Z or C.
	surf(Z) creates a a three-dimensional shaded surface from the z components in matrix Z, using $x = 1:n$ and $y = 1:m$, where $[m,n] = size(Z)$. The height, Z, is a single-valued function defined over a geometrically rectangular grid. Z specifies the color data as well as surface height, so color is proportional to surface height.
	surf(Z,C) plots the height of Z, a single-valued function defined over a geometrically rectangular grid, and uses matrix C, assumed to be the same size as Z, to color the surface.

	surf(X,Y,Z) creates a shaded surface using Z for the color data as well as surface height. X and Y are vectors or matrices defining the x and y components of a surface. If X and Y are vectors, $length(X) = n$ and length(Y) = m, where $[m,n] = size(Z)$. In this case, the vertices of the surface faces are $(X(j), Y(i), Z(i,j))$ triples. To create X and Y matrices for arbitrary domains, use the meshgrid function.
	surf(X,Y,Z,C) creates a shaded surface, with color defined by C. MATLAB performs a linear transformation on this data to obtain colors from the current colormap.
	<pre>surf(,'PropertyName',PropertyValue) specifies surface properties along with the data.</pre>
	<pre>surf(axes_handles,) and surfc(axes_handles,) plot into the axes with handle axes_handle instead of the current axes (gca).</pre>
	<pre>surfc() draws a contour plot beneath the surface.</pre>
	h = surf() and $h = surfc()$ return a handle to a surfaceplot graphics object.
Remarks	surf and surfc do not accept complex inputs.
Algorithm	Abstractly, a parametric surface is parameterized by two independent variables, i and j, which vary continuously over a rectangle; for example, $1 \le i \le m$ and $1 \le j \le n$. The three functions $x(i,j), y(i,j)$, and $z(i,j)$ specify the surface. When i and j are integer values, they define a rectangular grid with integer grid points. The functions $x(i,j), y(i,j)$, and $z(i,j)$, $y(i,j)$, and $z(i,j)$ become three m-by-n matrices, X, Y, and Z. Surface color is a fourth function, $c(i,j)$, denoted by matrix C.
	Each point in the rectangular grid can be thought of as connected to its four nearest neighbors.

This underlying rectangular grid induces four-sided patches on the surface. To express this another way, [X(:) Y(:) Z(:)] returns a list of triples specifying points in 3-space. Each interior point is connected to the four neighbors inherited from the matrix indexing. Points on the edge of the surface have three neighbors; the four points at the corners of the grid have only two neighbors. This defines a mesh of quadrilaterals or a *quad-mesh*.

Surface color can be specified in two different ways: at the vertices or at the centers of each patch. In this general setting, the surface need not be a single-valued function of x and y. Moreover, the four-sided surface patches need not be planar. For example, you can have surfaces defined in polar, cylindrical, and spherical coordinate systems.

The shading function sets the shading. If the shading is interp, C must be the same size as X, Y, and Z; it specifies the colors at the vertices. The color within a surface patch is a bilinear function of the local coordinates. If the shading is faceted (the default) or flat, C(i,j) specifies the constant color in the surface patch:

```
(i,j) - (i,j+1)
| C(i,j) |
(i+1,j) - (i+1,j+1)
```

In this case, C can be the same size as X, Y, and Z and its last row and column are ignored. Alternatively, its row and column dimensions can be one less than those of X, Y, and Z.

The surf and surfc functions specify the viewpoint using view(3).


The range of X, Y, and Z or the current setting of the axes XLimMode, YLimMode, and ZLimMode properties (also set by the axis function) determines the axis labels.

The range of C or the current setting of the axes CLim and CLimMode properties (also set by the caxis function) determines the color scaling. The scaled color values are used as indices into the current colormap.

surf, surfc


Examples Display a surfaceplot and contour plot of the peaks surface.

[X,Y,Z] = peaks(30); surfc(X,Y,Z) colormap hsv axis([-3 3 -3 3 -10 5])



Color a sphere with the pattern of +1s and -1s in a Hadamard matrix.

```
k = 5;
n = 2^k-1;
[x,y,z] = sphere(n);
c = hadamard(2^k);
surf(x,y,z,c);
```



See Also axis, caxis, colormap, contour, delaunay, imagesc, mesh, meshgrid, pcolor, shading, trisurf, view

Properties for surfaceplot graphics objects

"Surface and Mesh Creation" on page 1-107 for related functions

"Creating Mesh and Surface Plots" in the Getting Started with MATLAB documentation for background and examples.

Representing a Matrix as a Surface in the MATLAB 3-D Visualization documentation for further examples $\$

Coloring Mesh and Surface Plots for information about how to control the coloring of surfaces

Purpose	Convert surface data to patch data
Syntax	<pre>fvc = surf2patch(Z) fvc = surf2patch(Z,C) fvc = surf2patch(X,Y,Z) fvc = surf2patch(X,Y,Z,C) fvc = surf2patch(,'triangles') [f,v,c] = surf2patch()</pre>
Description	<pre>fvc = surf2patch(h)</pre>
	converts the geometry and color data from the surface object identified by the handle h into patch format and returns the face, vertex, and color data in the struct fvc. You can pass this struct directly to the patch command.
	fvc = surf2patch(Z) calculates the patch data from the surface's ZData matrix Z.
	fvc = surf2patch(Z,C) calculates the patch data from the surface's ZData and CData matrices Z and C.
	fvc = surf2patch(X,Y,Z) calculates the patch data from the surface's XData, YData, and ZData matrices X, Y, and Z.
	fvc = surf2patch(X,Y,Z,C) calculates the patch data from the surface's XData, YData, ZData, and CData matrices X, Y, Z, and C.
	<pre>fvc = surf2patch(,'triangles') creates triangular faces instead of the quadrilaterals that compose surfaces.</pre>
	[f,v,c] = surf2patch() returns the face, vertex, and color data in the three arrays f, v, and c instead of a struct.
Examples	The first example uses the sphere command to generate the XData, YData, and ZData of a surface, which is then converted to a patch. Note that the ZData (z) is passed to surf2patch as both the third and fourth arguments — the third argument is the ZData and the fourth argument is taken as the CData. This is because the patch command does not

automatically use the *z*-coordinate data for the color data, as does the surface command.

Also, because patch is a low-level command, you must set the view to 3-D and shading to faceted to produce the same results produced by the surf command.

```
[x y z] = sphere;
patch(surf2patch(x,y,z,z));
shading faceted; view(3)
```

In the second example surf2patch calculates face, vertex, and color data from a surface whose handle has been passed as an argument.

```
s = surf(peaks);
pause
patch(surf2patch(s));
delete(s)
shading faceted; view(3)
```

See Also patch, reducepatch, shrinkfaces, surface, surf

"Volume Visualization" on page 1-111 for related functions

Purpose	Create surface object
Syntax	<pre>surface(Z) surface(Z,C) surface(X,Y,Z) surface(X,Y,Z,C) surface(x,y,Z) surface('PropertyName',PropertyValue,) h = surface()</pre>
Properties	For a list of properties, see Surface Properties.
Description	surface is the low-level function for creating surface graphics objects. Surfaces are plots of matrix data created using the row and column indices of each element as the <i>x</i> - and <i>y</i> -coordinates and the value of each element as the <i>z</i> -coordinate.
	<pre>surface(Z) plots the surface specified by the matrix Z. Here, Z is a single-valued function, defined over a geometrically rectangular grid.</pre>
	<pre>surface(Z,C) plots the surface specified by Z and colors it according to the data in C (see "Examples").</pre>
	surface(X,Y,Z) uses $C = Z$, so color is proportional to surface height above the x-y plane.
	surface(X,Y,Z,C) plots the parametric surface specified by X, Y, and Z, with color specified by C.
	<pre>surface(x,y,Z), surface(x,y,Z,C) replaces the first two matrix arguments with vectors and must have length(x) = n and length(y) = m where [m,n] = size(Z). In this case, the vertices of the surface facets are the triples (x(j),y(i),Z(i,j)). Note that x corresponds to the columns of Z and y corresponds to the rows of Z. For a complete discussion of parametric surfaces, see the surf function.</pre>
	<pre>surface('PropertyName', PropertyValue,) follows the X, Y, Z, and C arguments with property name/property value pairs to specify</pre>

surface

additional surface properties. For a description of the properties, see Surface Properties.

h = surface(...) returns a handle to the created surface object.

Remarks surface does not respect the settings of the figure and axes NextPlot properties. It simply adds the surface object to the current axes.

If you do not specify separate color data (C), MATLAB uses the matrix (Z) to determine the coloring of the surface. In this case, color is proportional to values of Z. You can specify a separate matrix to color the surface independently of the data defining the area of the surface.

You can specify properties as property name/property value pairs, structure arrays, and cell arrays (see set and get for examples of how to specify these data types).

surface provides convenience forms that allow you to omit the property name for the XData, YData, ZData, and CData properties. For example,

```
surface('XData',X,'YData',Y,'ZData',Z,'CData',C)
```

is equivalent to

```
surface(X,Y,Z,C)
```

When you specify only a single matrix input argument,

surface(Z)

MATLAB assigns the data properties as if you specified

```
surface('XData',[1:size(Z,2)],...
'YData',[1:size(Z,1)],...
'ZData',Z,...
'CData',Z)
```

The axis, caxis, colormap, hold, shading, and view commands set graphics properties that affect surfaces. You can also set and query


surface property values after creating them using the set and get commands.

Example

This example creates a surface using peaks to generate the data, and colors it using the clown image. The ZData is a 49-by-49 element matrix, while the CData is a 200-by-320 matrix. You must set the surface's FaceColor to texturemap to use ZData and CData of different dimensions.

```
load clown
surface(peaks,flipud(X),...
'FaceColor','texturemap',...
'EdgeColor','none',...
'CDataMapping','direct')
colormap(map)
view(-35,45)
```

surface



Note the use of the surface(Z,C) convenience form combined with property name/property value pairs.

Since the clown data (X) is typically viewed with the image command, which MATLAB normally displays with 'ij' axis numbering and direct CDataMapping, this example reverses the data in the vertical direction using flipud and sets the CDataMapping property to direct.

Setting Default	You can set default surface properties on the axes, figure, and root object levels:
Properties	<pre>set(0,'DefaultSurfaceProperty',PropertyValue) set(gcf,'DefaultSurfaceProperty',PropertyValue) set(gca,'DefaultSurfaceProperty',PropertyValue)</pre>
	where <i>Property</i> is the name of the surface property whose default value you want to set and PropertyValue is the value you are specifying. Use set and get to access the surface properties.
See Also	ColorSpec, patch, pcolor, surf
	Surface Properties for property descriptions
	"Surface and Mesh Creation" on page 1-107 and "Object Creation" on page 1-104 for related functions
Tutorials	For examples, see Representing a Matrix as a Surface.

Surface Properties

Purpose	Surface properties		
Creating Surface Objects	Use surface to create surface objects.		
Modifying Properties	 You can set and query graphics object properties in two ways: The Property Editor is an interactive tool that enables you to see and change object property values. The set and get commands enable you to set and query the values of properties. To change the default values of properties, see Setting Default Property Values. See "Core Graphics Objects" for general information about this type of object. 		
Surface Property Descriptions	 This section lists property names along with the types of values each accepts. Curly braces {} enclose default values. AlphaData m-by-n matrix of double or uint8 The transparency data. A matrix of non-NaN values specifying the transparency of each face or vertex of the object. The AlphaData can be of class double or uint8. MATLAB software determines the transparency in one of three ways: Using the elements of AlphaData as transparency values (AlphaDataMapping set to none) Using the elements of AlphaData as indices into the current alphamap (AlphaDataMapping set to direct) 		

• Scaling the elements of AlphaData to range between the minimum and maximum values of the axes ALim property (AlphaDataMapping set to scaled, the default)

AlphaDataMapping

none | direct | {scaled}

Transparency mapping method. This property determines how MATLAB interprets indexed alpha data. This property can be any of the following:

- none The transparency values of AlphaData are between 0 and 1 or are clamped to this range (the default).
- scaled Transform the AlphaData to span the portion of the alphamap indicated by the axes ALim property, linearly mapping data values to alpha values.
- direct use the AlphaData as indices directly into the alphamap. When not scaled, the data are usually integer values ranging from 1 to length(alphamap). MATLAB maps values less than 1 to the first alpha value in the alphamap, and values greater than length(alphamap) to the last alpha value in the alphamap. Values with a decimal portion are fixed to the nearest lower integer. If AlphaData is an array of uint8 integers, then the indexing begins at 0 (i.e., MATLAB maps a value of 0 to the first alpha value in the alphamap).

AmbientStrength

scalar ≥ 0 and ≤ 1

Strength of ambient light. This property sets the strength of the ambient light, which is a nondirectional light source that illuminates the entire scene. You must have at least one visible light object in the axes for the ambient light to be visible. The axes AmbientLightColor property sets the color of the ambient light, which is therefore the same on all objects in the axes. You can also set the strength of the diffuse and specular contribution of light objects. See the surface DiffuseStrength and SpecularStrength properties.

Annotation

hg.Annotation object Read Only

Control the display of surface objects in legends. The Annotation property enables you to specify whether this surface object is represented in a figure legend.

Querying the Annotation property returns the handle of an hg.Annotation object. The hg.Annotation object has a property called LegendInformation, which contains an hg.LegendEntry object.

Once you have obtained the hg.LegendEntry object, you can set its IconDisplayStyle property to control whether the surface object is displayed in a figure legend:

IconDisplayStyle Value	Purpose
on	Represent this surface object in a legend (default)
off	Do not include this surface object in a legend
children	Same as on because surface objects do not have children

Setting the IconDisplayStyle property

These commands set the IconDisplayStyle of a graphics object with handle hobj to off:

```
hAnnotation = get(hobj, 'Annotation');
hLegendEntry = get(hAnnotation', 'LegendInformation');
set(hLegendEntry, 'IconDisplayStyle', 'off')
```

Using the IconDisplayStyle property

See "Controlling Legends" for more information and examples.

BackFaceLighting unlit | lit | reverselit

Face lighting control. This property determines how faces are lit when their vertex normals point away from the camera.

- unlit Face is not lit.
- lit Face is lit in normal way.
- reverselit Face is lit as if the vertex pointed towards the camera.

This property is useful for discriminating between the internal and external surfaces of an object. See "Back Face Lighting" for an example.

BeingDeleted

on | {off} Read Only

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions may not need to perform actions on objects that are going to be deleted, and therefore, can check the object's BeingDeleted property before acting.

BusyAction

cancel | {queue}

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callback routines. If there is a callback routine executing, callback routines invoked subsequently always attempt to interrupt it. If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are

- cancel Discard the event that attempted to execute a second callback routine.
- queue Queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Button press callback function. A callback function that executes whenever you press a mouse button while the pointer is over the surface object.

See the figure's SelectionType property to determine if modifier keys were also pressed.

Set this property to a function handle that references the callback. The function must define at least two input arguments (handle of object associated with the button down event and an event structure, which is empty for this property). For example, the following function takes different action depending on what type of selection was made:

```
function button_down(src,evnt)
% src - the object that is the source of the event
% evnt - empty for this property
    sel typ = get(gcbf,'SelectionType')
```

```
switch sel_typ
case 'normal'
disp('User clicked left-mouse button')
set(src,'Selected','on')
case 'extend'
disp('User did a shift-click')
set(src,'Selected','on')
case 'alt'
disp('User did a control-click')
set(src,'Selected','on')
set(src,'Selected','on')
set(src,'SelectionHighlight','off')
end
end
```

Suppose h is the handle of a surface object and that the button_down function is on your MATLAB path. The following statement assigns the function above to the ButtonDownFcn:

set(h, 'ButtonDownFcn',@button_down)

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

CData

matrix (of type double)

Vertex colors. A matrix containing values that specify the color at every point in ZData.

Mapping CData to a Colormap

You can specify color as indexed values or true color. Indexed color data specifies a single value for each vertex. These values are either scaled to map linearly into the current colormap (see caxis) or interpreted directly as indices into the colormap, depending on the setting of the CDataMapping property.

CData as True Color

True color defines an RGB value for each vertex. If the coordinate data (XData, for example) are contained in m-by-n matrices, then CData must be an m-by-n-3 array. The first page contains the red components, the second the green components, and the third the blue components of the colors.

Texturemapping the Surface FaceColor

If you set the FaceColor property to texturemap, CData does not need to be the same size as ZData, but must be of type double or uint8. In this case, MATLAB maps CData to conform to the surface defined by ZData.

```
CDataMapping
```

{scaled} | direct

Direct or scaled color mapping. This property determines how MATLAB interprets indexed color data used to color the surface. (If you use true color specification for CData, this property has no effect.)

- scaled Transform the color data to span the portion of the colormap indicated by the axes CLim property, linearly mapping data values to colors. See the caxis reference page for more information on this mapping.
- direct Use the color data as indices directly into the colormap. The color data should then be integer values ranging from 1 to length(colormap). MATLAB maps values less than 1 to the first color in the colormap, and values greater than length(colormap) to the last color in the colormap. Values with a decimal portion are fixed to the nearest lower integer.

Children

matrix of handles

Always the empty matrix; surface objects have no children.

Clipping

 $\{on\} \mid off$

Clipping to axes rectangle. When Clipping is on, MATLAB does not display any portion of the surface that is outside the axes rectangle.

CreateFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Callback function executed during object creation. This property defines a callback function that executes when MATLAB creates a surface object. You must define this property as a default value for surfaces or set the CreateFcn property during object creation.

For example, the following statement creates a surface (assuming x, y, z, and c are defined), and executes the function referenced by the function handle @myCreateFcn.

surface(x,y,z,c,'CreateFcn',@myCreateFcn)

MATLAB executes this routine after setting all surface properties. Setting this property on an existing surface object has no effect.

The handle of the object whose CreateFcn is being executed is passed by MATLAB as the first argument to the callback function and is also accessible through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DeleteFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Delete surface callback function. A callback function that executes when you delete the surface object (for example, when you issue a delete command or clear the axes cla or figure clf). For example, the following function displays object property data before the object is deleted.

```
function delete_fcn(src,evnt)
% src - the object that is the source of the event
% evnt - empty for this property
   obj_tp = get(src,'Type');
   disp([obj_tp, ' object deleted'])
   disp('Its user data is:')
   disp(get(src,'UserData'))
end
```

MATLAB executes the function before deleting the object's properties so these values are available to the callback function. The function must define at least two input arguments (handle of object being deleted and an event structure, which is empty for this property)

The handle of the object whose DeleteFcn is being executed is passed by MATLAB as the first argument to the callback function and is also accessible through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DiffuseStrength

scalar ≥ 0 and ≤ 1

Intensity of diffuse light. This property sets the intensity of the diffuse component of the light falling on the surface. Diffuse light comes from light objects in the axes.

You can also set the intensity of the ambient and specular components of the light on the surface object. See the AmbientStrength and SpecularStrength properties.

DisplayName

string (default is empty string)

String used by legend for this surface object. The legend function uses the string defined by the DisplayName property to label this surface object in the legend.

- If you specify string arguments with the legend function, DisplayName is set to this surface object's corresponding string and that string is used for the legend.
- If DisplayName is empty, legend creates a string of the form, ['data' n], where n is the number assigned to the object based on its location in the list of legend entries. However, legend does not set DisplayName to this string.
- If you edit the string directly in an existing legend, DisplayName is set to the edited string.
- If you specify a string for the DisplayName property and create the legend using the figure toolbar, then MATLAB uses the string defined by DisplayName.
- To add programmatically a legend that uses the DisplayName string, call legend with the toggle or show option.

See "Controlling Legends" for more examples.

EdgeAlpha

{scalar = 1} | flat | interp

Transparency of the surface edges. This property can be any of the following:

• scalar — A single non-Nan scalar value between 0 and 1 that controls the transparency of all the edges of the object.

 $1 \ (the \ default)$ means fully opaque and $0 \ means$ completely transparent.

- flat The alpha data (AlphaData) value for the first vertex of the face determines the transparency of the edges.
- interp Linear interpolation of the alpha data (AlphaData) values at each vertex determines the transparency of the edge.


Note that you must specify AlphaData as a matrix equal in size to ZData to use flat or interp EdgeAlpha.

EdgeColor

{ColorSpec} | none | flat | interp

Color of the surface edge. This property determines how MATLAB colors the edges of the individual faces that make up the surface:

- ColorSpec A three-element RGB vector or one of the MATLAB predefined names, specifying a single color for edges. The default EdgeColor is black. See ColorSpec for more information on specifying color.
- none Edges are not drawn.
- flat The CData value of the first vertex for a face determines the color of each edge.



• interp — Linear interpolation of the CData values at the face vertices determines the edge color.

EdgeLighting

{none} | flat | gouraud | phong

Algorithm used for lighting calculations. This property selects the algorithm used to calculate the effect of light objects on surface edges. Choices are

- none Lights do not affect the edges of this object.
- flat The effect of light objects is uniform across each edge of the surface.
- gouraud The effect of light objects is calculated at the vertices and then linearly interpolated across the edge lines.
- phong The effect of light objects is determined by interpolating the vertex normals across each edge line and calculating the reflectance at each pixel. Phong lighting generally produces better results than Gouraud lighting, but takes longer to render.

EraseMode

{normal} | none | xor | background

Erase mode. This property controls the technique MATLAB uses to draw and erase surface objects. Alternative erase modes are useful for creating animated sequences, where control of the way individual objects are redrawn is necessary to improve performance and obtain the desired effect.

• normal — Redraw the affected region of the display, performing the three-dimensional analysis necessary to ensure that all objects are rendered correctly. This mode produces the most accurate picture, but is the slowest. The other modes are faster, but do not perform a complete redraw and are therefore less accurate.

- none Do not erase the surface when it is moved or destroyed. While the object is still visible on the screen after erasing with EraseMode none, you cannot print it because MATLAB stores no information about its former location.
- xor Draw and erase the surface by performing an exclusive OR (XOR) with each pixel index of the screen behind it. Erasing the surface does not damage the color of the objects behind it. However, surface color depends on the color of the screen behind it and is correctly colored only when over the axes background Color, or the figure background Color if the axes Color is set to none.
- background Erase the surface by drawing it in the axes background Color, or the figure background Color if the axes Color is set to none. This damages objects that are behind the erased object, but surface objects are always properly colored.

Printing with Nonnormal Erase Modes

MATLAB always prints figures as if the EraseMode of all objects is normal. This means graphics objects created with EraseMode set to none, xor, or background can look different on screen than on paper. On screen, MATLAB may mathematically combine layers of colors (for example, performing an XOR of a pixel color with that of the pixel behind it) and ignore three-dimensional sorting to obtain greater rendering speed. However, these techniques are not applied to the printed output.

You can use the MATLAB getframe command or other screen capture application to create an image of a figure containing nonnormal mode objects.

FaceAlpha

{scalar = 1} | flat | interp | texturemap

Transparency of the surface faces. This property can be any of the following:

- scalar A single non-NaN scalar value between 0 and 1 that controls the transparency of all the faces of the object.
 1 (the default) means fully opaque and 0 means completely transparent (invisible).
- flat The values of the alpha data (AlphaData) determine the transparency for each face. The alpha data at the first vertex determine the transparency of the entire face.
- interp Bilinear interpolation of the alpha data (AlphaData) at each vertex determines the transparency of each face.
- texturemap Use transparency for the texture map.

Note that you must specify AlphaData as a matrix equal in size to ZData to use flat or interp FaceAlpha.

FaceColor

ColorSpec | none | {flat} | interp | texturemap

Color of the surface face. This property can be any of the following:

- ColorSpec A three-element RGB vector or one of the MATLAB predefined names, specifying a single color for faces. See ColorSpec for more information on specifying color.
- none Do not draw faces. Note that edges are drawn independently of faces.
- flat The values of CData determine the color for each face of the surface. The color data at the first vertex determine the color of the entire face.
- interp Bilinear interpolation of the values at each vertex (the CData) determines the coloring of each face.
- texturemap Texture map the CData to the surface. MATLAB transforms the color data so that it conforms to the surface. (See the texture mapping example.)

FaceLighting

{none} | flat | gouraud | phong

Algorithm used for lighting calculations. This property selects the algorithm used to calculate the effect of light objects on the surface. Choices are

- none Lights do not affect the faces of this object.
- flat The effect of light objects is uniform across the faces of the surface. Select this choice to view faceted objects.
- gouraud The effect of light objects is calculated at the vertices and then linearly interpolated across the faces. Select this choice to view curved surfaces.
- phong The effect of light objects is determined by interpolating the vertex normals across each face and calculating the reflectance at each pixel. Select this choice to view curved surfaces. Phong lighting generally produces better results than Gouraud lighting, but takes longer to render.

HandleVisibility

{on} | callback | off

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. This property is useful for preventing command-line users from accidentally drawing into or deleting a figure that contains only user interface devices (such as a dialog box).

Handles are always visible when HandleVisibility is on.

Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles. Setting HandleVisibility to off makes handles invisible at all times. This might be necessary when a callback routine invokes a function that could potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close.

When a handle's visibility is restricted using callback or off, the object's handle does not appear in its parent's Children property, figures do not appear in the root's CurrentFigure property, objects do not appear in the root's CallbackObject property or in the figure's CurrentObject property, and axes do not appear in their parent's CurrentAxes property.

You can set the root ShowHiddenHandles property to on to make all handles visible, regardless of their HandleVisibility settings (this does not affect the values of the HandleVisibility properties).

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

HitTest

{on} | off

Selectable by mouse click. HitTest determines if the surface can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click on the surface. If HitTest is off, clicking on the surface selects the object below it (which may be the axes containing it).

Interruptible

{on} | off

Callback routine interruption mode. The Interruptible property controls whether a surface callback routine can be interrupted by subsequently invoked callback routines. Only callback routines defined for the ButtonDownFcn are affected by the Interruptible property. MATLAB checks for events that can interrupt a callback routine only when it encounters a drawnow, figure, getframe, or pause command in the routine. See the BusyAction property for related information.

LineStyle

{-} | -- | : | -. | none

Edge line type. This property determines the line style used to draw surface edges. The available line styles are shown in this table.

Symbol	Line Style
	Solid line (default)
	Dashed line
:	Dotted line
	Dash-dot line
none	No line

LineWidth

scalar

Edge line width. The width of the lines in points used to draw surface edges. The default width is 0.5 points (1 point = 1/72 inch).

Marker

marker symbol (see table)

Marker symbol. The Marker property specifies symbols that are displayed at vertices. You can set values for the Marker property independently from the LineStyle property.

Marker Specifier	Description
+	Plus sign
0	Circle
*	Asterisk
	Point
x	Cross
S	Square
d	Diamond
^	Upward-pointing triangle
V	Downward-pointing triangle
>	Right-pointing triangle
<	Left-pointing triangle
р	Five-pointed star (pentagram)
h	Six-pointed star (hexagram)
none	No marker (default)

You can specify these markers.

MarkerEdgeColor

none | {auto} | flat | ColorSpec

Marker edge color. The color of the marker or the edge color for filled markers (circle, square, diamond, pentagram, hexagram, and the four triangles).

- none specifies no color, which makes nonfilled markers invisible.
- auto uses the same color as the EdgeColor property.
- flat uses the CData value of the vertex to determine the color of the maker edge.

• ColorSpec defines a single color to use for the edge (see ColorSpec for more information).

MarkerFaceColor

{none} | auto | flat | ColorSpec

Marker face color. The fill color for markers that are closed shapes (circle, square, diamond, pentagram, hexagram, and the four triangles).

- none makes the interior of the marker transparent, allowing the background to show through.
- auto uses the axes Color for the marker face color.
- flat uses the CData value of the vertex to determine the color of the face.
- ColorSpec defines a single color to use for all markers on the surface (see ColorSpec for more information).

MarkerSize

size in points

Marker size. A scalar specifying the marker size, in points. The default value for MarkerSize is 6 points (1 point = 1/72 inch). Note that MATLAB draws the point marker at 1/3 the specified marker size.

MeshStyle

{both} | row | column

Row and column lines. This property specifies whether to draw all edge lines or just row or column edge lines.

- both draws edges for both rows and columns.
- row draws row edges only.
- column draws column edges only.

NormalMode

{auto} | manual

MATLAB generated or user-specified normal vectors. When this property is auto, MATLAB calculates vertex normals based on the coordinate data. If you specify your own vertex normals, MATLAB sets this property to manual and does not generate its own data. See also the VertexNormals property.

Parent

handle of axes, hggroup, or hgtransform

Parent of surface object. This property contains the handle of the surface object's parent. The parent of a surface object is the axes, hggroup, or hgtransform object that contains it.

See "Objects That Can Contain Other Objects" for more information on parenting graphics objects.

Selected

on | {off}

Is object selected? When this property is on, MATLAB displays a dashed bounding box around the surface if the SelectionHighlight property is also on. You can, for example, define the ButtonDownFcn to set this property, allowing users to select the object with the mouse.

SelectionHighlight

{on} | off

Objects are highlighted when selected. When the Selected property is on, MATLAB indicates the selected state by drawing a dashed bounding box around the surface. When SelectionHighlight is off, MATLAB does not draw the handles.

SpecularColorReflectance

scalar in the range 0 to 1

Color of specularly reflected light. When this property is 0, the color of the specularly reflected light depends on both the color of the object from which it reflects and the color of the light source. When set to 1, the color of the specularly reflected light depends only on the color or the light source (i.e., the light object Color property). The proportions vary linearly for values in between.

SpecularExponent

scalar ≥ 1

Harshness of specular reflection. This property controls the size of the specular spot. Most materials have exponents in the range of 5 to 20.

SpecularStrength

scalar ≥ 0 and ≤ 1

Intensity of specular light. This property sets the intensity of the specular component of the light falling on the surface. Specular light comes from light objects in the axes.

You can also set the intensity of the ambient and diffuse components of the light on the surface object. See the AmbientStrength and DiffuseStrength properties. Also see the material function.

Тад

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when you are constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callback routines. You can define Tag as any string.

Туре

string (read only)

Class of the graphics object. The class of the graphics object. For surface objects, Type is always the string 'surface'.

UIContextMenu

handle of a uicontextmenu object

Associate a context menu with the surface. Assign this property the handle of a uicontextmenu object created in the same figure as the surface. Use the uicontextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click over the surface.

UserData

matrix

User-specified data. Any matrix you want to associate with the surface object. MATLAB does not use this data, but you can access it using the set and get commands.

VertexNormals

vector or matrix

Surface normal vectors. This property contains the vertex normals for the surface. MATLAB generates this data to perform lighting calculations. You can supply your own vertex normal data, even if it does not match the coordinate data. This can be useful to produce interesting lighting effects.

Visible

{on} | off

Surface object visibility. By default, all surfaces are visible. When set to off, the surface is not visible, but still exists, and you can query and set its properties.

XData

vector or matrix

X-coordinates. The *x*-position of the surface points. If you specify a row vector, **surface** replicates the row internally until it has the same number of columns as ZData.

YData

vector or matrix

Y-coordinates. The *y*-position of the surface points. If you specify a row vector, **surface** replicates the row internally until it has the same number of rows as ZData.

ZData

matrix

Z-coordinates. The z-position of the surface plot data points. See the Description section for more information.

See Also surface

Purpose Define surfaceplot properties

Modifying Properties

You can set and query graphics object properties in two ways:

- The Property Editor is an interactive tool that enables you to see and change object property values.
- The set and get commands enable you to set and query the values of properties.

Note that you cannot define default properties for surfaceplot objects.

See Plot Objects for information on surfaceplot objects.

Surfaceplot Property Descriptions

This section lists property names along with the types of values each accepts. Curly braces {} enclose default values.

AlphaData

m-by-n matrix of double or uint8

The transparency data. A matrix of non-NaN values specifying the transparency of each face or vertex of the object. The AlphaData can be of class double or uint8.

MATLAB software determines the transparency in one of three ways:

- Using the elements of AlphaData as transparency values (AlphaDataMapping set to none)
- Using the elements of AlphaData as indices into the current alphamap (AlphaDataMapping set to direct)
- Scaling the elements of AlphaData to range between the minimum and maximum values of the axes ALim property (AlphaDataMapping set to scaled, the default)

AlphaDataMapping

{none} | direct| scaled

Transparency mapping method. This property determines how MATLAB interprets indexed alpha data. It can be any of the following:

- none The transparency values of AlphaData are between 0 and 1 or are clamped to this range (the default).
- scaled Transform the AlphaData to span the portion of the alphamap indicated by the axes ALim property, linearly mapping data values to alpha values.
- direct Use the AlphaData as indices directly into the alphamap. When not scaled, the data are usually integer values ranging from 1 to length(alphamap). MATLAB maps values less than 1 to the first alpha value in the alphamap, and values greater than length(alphamap) to the last alpha value in the alphamap. Values with a decimal portion are fixed to the nearest, lower integer. If AlphaData is an array of uint8 integers, then the indexing begins at 0 (i.e., MATLAB maps a value of 0 to the first alpha value in the alphamap).

AmbientStrength

scalar ≥ 0 and ≤ 1

Strength of ambient light. This property sets the strength of the ambient light, which is a nondirectional light source that illuminates the entire scene. You must have at least one visible light object in the axes for the ambient light to be visible. The axes AmbientLightColor property sets the color of the ambient light, which is therefore the same on all objects in the axes.

You can also set the strength of the diffuse and specular contribution of light objects. See the surfaceplot DiffuseStrength and SpecularStrength properties.

Annotation

hg.Annotation object Read Only

Control the display of surfaceplot objects in legends. The Annotation property enables you to specify whether this surfaceplot object is represented in a figure legend.

Querying the Annotation property returns the handle of an hg.Annotation object. The hg.Annotation object has a property called LegendInformation, which contains an hg.LegendEntry object.

Once you have obtained the hg.LegendEntry object, you can set its IconDisplayStyle property to control whether the surfaceplot object is displayed in a figure legend:

IconDisplayStyle Value	Purpose
on	Represent this surfaceplot object in a legend (default)
off	Do not include this surfaceplot object in a legend
children	Same as on because surfaceplot objects do not have children

Setting the IconDisplayStyle property

These commands set the IconDisplayStyle of a graphics object with handle hobj to off:

```
hAnnotation = get(hobj, 'Annotation');
hLegendEntry = get(hAnnotation', 'LegendInformation');
set(hLegendEntry, 'IconDisplayStyle', 'off')
```

Using the IconDisplayStyle property

See "Controlling Legends" for more information and examples.

```
BackFaceLighting
unlit | lit | reverselit
```

Face lighting control. This property determines how faces are lit when their vertex normals point away from the camera.

- unlit Face is not lit.
- lit Face is lit in normal way.
- reverselit Face is lit as if the vertex pointed towards the camera.

This property is useful for discriminating between the internal and external surfaces of an object. See Back Face Lighting for an example.

BeingDeleted

on | {off} Read Only

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions might not need to perform actions on objects if the objects are going to be deleted, and therefore, can check the object's BeingDeleted property before acting.

```
BusyAction
```

cancel | {queue}

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callbacks. If there is a callback function

executing, callbacks invoked subsequently always attempt to interrupt it.

If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are

- cancel Discard the event that attempted to execute a second callback routine.
- queue Queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn

cancel | {queue}

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callbacks. If there is a callback function executing, callbacks invoked subsequently always attempt to interrupt it.

If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are

- cancel Discard the event that attempted to execute a second callback routine.
- queue Queue the event that attempted to execute a second callback routine until the current callback finishes.

CData matrix

> *Vertex colors.* A matrix containing values that specify the color at every point in ZData. If you set the FaceColor property to texturemap, CData does not need to be the same size as ZData. In this case, MATLAB maps CData to conform to the surfaceplot defined by ZData.

You can specify color as indexed values or true color. Indexed color data specifies a single value for each vertex. These values are either scaled to map linearly into the current colormap (see caxis) or interpreted directly as indices into the colormap, depending on the setting of the CDataMapping property. Note that any non-texture data passed as an input argument must be of type double.

True color defines an RGB value for each vertex. If the coordinate data (XData, for example) are contained in m-by-n matrices, then CData must be an m-by-n-by-3 array. The first page contains the red components, the second the green components, and the third the blue components of the colors.

```
CDataMapping
```

{scaled} | direct

Direct or scaled color mapping. This property determines how MATLAB interprets indexed color data used to color the surfaceplot. (If you use true color specification for CData, this property has no effect.)

- scaled Transform the color data to span the portion of the colormap indicated by the axes CLim property, linearly mapping data values to colors. See the caxis reference page for more information on this mapping.
- direct Use the color data as indices directly into the colormap. The color data should then be integer values ranging

from 1 to length(colormap). MATLAB maps values less than 1 to the first color in the colormap, and values greater than length(colormap) to the last color in the colormap. Values with a decimal portion are fixed to the nearest lower integer.

CDataMode

{auto} | manual

Use automatic or user-specified color data values. If you specify CData, MATLAB sets this property to manual and uses the CData values to color the surfaceplot.

If you set CDataMode to auto after having specified CData, MATLAB resets the color data of the surfaceplot to that defined by ZData, overwriting any previous values for CData.

CDataSource

string (MATLAB variable)

Link CData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the CData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change CData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to return data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

Children

matrix of handles

Always the empty matrix; surfaceplot objects have no children.

Clipping

{on} | off

Clipping to axes rectangle. When Clipping is on, MATLAB does not display any portion of the surfaceplot that is outside the axes rectangle.

CreateFcn

string or function handle

Callback routine executed during object creation. This property defines a callback that executes when MATLAB creates an object. You must specify the callback during the creation of the object. For example,

graphicfcn(y, 'CreateFcn',@CallbackFcn)

where @CallbackFcn is a function handle that references the callback function and graphicfcn is the plotting function which creates this object.

MATLAB executes this routine after setting all other object properties. Setting this property on an existing object has no effect. The handle of the object whose CreateFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DeleteFcn

string or function handle

Callback executed during object deletion. A callback that executes when this object is deleted (e.g., this might happen when you issue a delete command on the object, its parent axes, or the figure containing it). MATLAB executes the callback before destroying the object's properties so the callback routine can query these values.

The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which can be queried using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

See the BeingDeleted property for related information.

DiffuseStrength

scalar ≥ 0 and ≤ 1

Intensity of diffuse light. This property sets the intensity of the diffuse component of the light falling on the surface. Diffuse light comes from light objects in the axes.

You can also set the intensity of the ambient and specular components of the light on the object. See the AmbientStrength and SpecularStrength properties.

DisplayName string (default is empty string)

String used by legend for this surfaceplot object. The legend function uses the string defined by the DisplayName property to label this surfaceplot object in the legend.

- If you specify string arguments with the legend function, DisplayName is set to this surfaceplot object's corresponding string and that string is used for the legend.
- If DisplayName is empty, legend creates a string of the form, ['data' n], where n is the number assigned to the object based on its location in the list of legend entries. However, legend does not set DisplayName to this string.
- If you edit the string directly in an existing legend, DisplayName is set to the edited string.
- If you specify a string for the DisplayName property and create the legend using the figure toolbar, then MATLAB uses the string defined by DisplayName.
- To add programmatically a legend that uses the DisplayName string, call legend with the toggle or show option.

See "Controlling Legends" for more examples.

EdgeAlpha

{scalar = 1} | flat | interp

Transparency of the patch and surface edges. This property can be any of the following:

- scalar A single non-Nan scalar value between 0 and 1 that controls the transparency of all the edges of the object.
 1 (the default) means fully opaque and 0 means completely transparent.
- flat The alpha data (AlphaData) value for the first vertex of the face determines the transparency of the edges.

• interp — Linear interpolation of the alpha data (AlphaData) values at each vertex determines the transparency of the edge.


Note that you must specify AlphaData as a matrix equal in size to ZData to use flat or interp EdgeAlpha.

EdgeColor

{ColorSpec} | none | flat | interp

Color of the surfaceplot edge. This property determines how MATLAB colors the edges of the individual faces that make up the surface:

- ColorSpec A three-element RGB vector or one of the MATLAB predefined names, specifying a single color for edges. The default EdgeColor is black. See ColorSpec for more information on specifying color.
- none Edges are not drawn.
- flat The CData value of the first vertex for a face determines the color of each edge.



• interp — Linear interpolation of the CData values at the face vertices determines the edge color.

```
EdgeLighting
{none} | flat | gouraud | phong
```

Algorithm used for lighting calculations. This property selects the algorithm used to calculate the effect of light objects on surfaceplot edges. Choices are

- none Lights do not affect the edges of this object.
- flat The effect of light objects is uniform across each edge of the surface.
- gouraud The effect of light objects is calculated at the vertices and then linearly interpolated across the edge lines.
- phong The effect of light objects is determined by interpolating the vertex normals across each edge line and calculating the reflectance at each pixel. Phong lighting generally produces better results than Gouraud lighting, but takes longer to render.

EraseMode

{normal} | none | xor | background

Erase mode. This property controls the technique MATLAB uses to draw and erase objects and their children. Alternative erase modes are useful for creating animated sequences, where control of the way individual objects are redrawn is necessary to improve performance and obtain the desired effect.

- normal Redraw the affected region of the display, performing the three-dimensional analysis necessary to ensure that all objects are rendered correctly. This mode produces the most accurate picture, but is the slowest. The other modes are faster, but do not perform a complete redraw and are therefore less accurate.
- none Do not erase objects when they are moved or destroyed.
 While the objects are still visible on the screen after erasing

with EraseMode none, you cannot print these objects because MATLAB stores no information about their former locations.

- xor Draw and erase the object by performing an exclusive OR (XOR) with each pixel index of the screen behind it. Erasing the object does not damage the color of the objects behind it. However, the color of the erased object depends on the color of the screen behind it and it is correctly colored only when it is over the axes background color (or the figure background color if the axes Color property is set to none). That is, it isn't erased correctly if there are objects behind it.
- background Erase the graphics objects by redrawing them in the axes background color, (or the figure background color if the axes Color property is set to none). This damages other graphics objects that are behind the erased object, but the erased object is always properly colored.

Printing with Nonnormal Erase Modes

MATLAB always prints figures as if the EraseMode of all objects is normal. This means graphics objects created with EraseMode set to none, xor, or background can look different on screen than on paper. On screen, MATLAB can mathematically combine layers of colors (e.g., performing an XOR on a pixel color with that of the pixel behind it) and ignore three-dimensional sorting to obtain greater rendering speed. However, these techniques are not applied to the printed output.

Set the axes background color with the axes Color property. Set the figure background color with the figure Color property.

You can use the MATLAB getframe command or other screen capture applications to create an image of a figure containing nonnormal mode objects.

FaceAlpha

{scalar = 1} | flat | interp | texturemap

Transparency of the surfaceplot faces. This property can be any of the following:

- scalar A single non-NaN scalar value between 0 and 1 that controls the transparency of all the faces of the object.
 1 (the default) means fully opaque and 0 means completely transparent (invisible).
- flat The values of the alpha data (AlphaData) determine the transparency for each face. The alpha data at the first vertex determine the transparency of the entire face.
- interp Bilinear interpolation of the alpha data (AlphaData) at each vertex determines the transparency of each face.
- texturemap Use transparency for the texture map.

Note that you must specify AlphaData as a matrix equal in size to ZData to use flat or interp FaceAlpha.

FaceColor

ColorSpec | none | {flat} | interp

Color of the surfaceplot face. This property can be any of the following:

- ColorSpec A three-element RGB vector or one of the MATLAB predefined names, specifying a single color for faces. See ColorSpec for more information on specifying color.
- none Do not draw faces. Note that edges are drawn independently of faces.
- flat The values of CData determine the color for each face of the surface. The color data at the first vertex determine the color of the entire face.
- interp Bilinear interpolation of the values at each vertex (the CData) determines the coloring of each face.

• texturemap — Texture map the Cdata to the surface. MATLAB transforms the color data so that it conforms to the surface. (See the texture mapping example for surface.)

FaceLighting

{none} | flat | gouraud | phong

Algorithm used for lighting calculations. This property selects the algorithm used to calculate the effect of light objects on the surface. Choices are

- none Lights do not affect the faces of this object.
- flat The effect of light objects is uniform across the faces of the surface. Select this choice to view faceted objects.
- gouraud The effect of light objects is calculated at the vertices and then linearly interpolated across the faces. Select this choice to view curved surfaces.
- phong The effect of light objects is determined by interpolating the vertex normals across each face and calculating the reflectance at each pixel. Select this choice to view curved surfaces. Phong lighting generally produces better results than Gouraud lighting, but takes longer to render.

HandleVisibility

{on} | callback | off

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally accessing objects that you need to protect for some reason.

- on Handles are always visible when HandleVisibility is on.
- callback Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to

protect GUIs from command-line users, while allowing callback routines to have access to object handles.

• off — Setting HandleVisibility to off makes handles invisible at all times. This might be necessary when a callback invokes a function that might potentially damage the GUI (such as evaluating a user-typed string) and so temporarily hides its own handles during the execution of that function.

Functions Affected by Handle Visibility

When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close.

Properties Affected by Handle Visibility

When a handle's visibility is restricted using callback or off, the object's handle does not appear in its parent's Children property, figures do not appear in the root's CurrentFigure property, objects do not appear in the root's CallbackObject property or in the figure's CurrentObject property, and axes do not appear in their parent's CurrentAxes property.

Overriding Handle Visibility

You can set the root ShowHiddenHandles property to on to make all handles visible regardless of their HandleVisibility settings (this does not affect the values of the HandleVisibility properties). See also findall.

Handle Validity

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties and pass it to any function that operates on handles.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

HitTest

{on} | off

Selectable by mouse click. HitTest determines whether this object can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click on the objects that compose the area graph. If HitTest is off, clicking this object selects the object below it (which is usually the axes containing it).

Interruptible

{on} | off

Callback routine interruption mode. The Interruptible property controls whether an object's callback can be interrupted by callbacks invoked subsequently.

Only callbacks defined for the ButtonDownFcn property are affected by the Interruptible property. MATLAB checks for events that can interrupt a callback only when it encounters a drawnow, figure, getframe, or pause command in the routine. See the BusyAction property for related information.

Setting Interruptible to on allows any graphics object's callback to interrupt callback routines originating from a bar property. Note that MATLAB does not save the state of variables or the display (e.g., the handle returned by the gca or gcf command) when an interruption occurs.

LineStyle

{-} | -- | : | -. | none

Line style. This property specifies the line style of the object. Available line styles are shown in the following table.

Specifier String	Line Style
-	Solid line (default)
	Dashed line
:	Dotted line
	Dash-dot line
none	No line

You can use LineStyle none when you want to place a marker at each point but do not want the points connected with a line (see the Marker property).

LineWidth

scalar

The width of linear objects and edges of filled areas. Specify this value in points (1 point = $1/_{72}$ inch). The default LineWidth is 0.5 points.

Marker

character (see table)

Marker symbol. The Marker property specifies the type of markers that are displayed at plot vertices. You can set values for the Marker property independently from the LineStyle property. Supported markers include those shown in the following table.

Marker Specifier	Description
+	Plus sign
0	Circle

Marker Specifier	Description
*	Asterisk
	Point
x	Cross
S	Square
d	Diamond
^	Upward-pointing triangle
v	Downward-pointing triangle
>	Right-pointing triangle
<	Left-pointing triangle
р	Five-pointed star (pentagram)
h	Six-pointed star (hexagram)
none	No marker (default)

MarkerEdgeColor

none | {auto} | flat | ColorSpec

Marker edge color. The color of the marker or the edge color for filled markers (circle, square, diamond, pentagram, hexagram, and the four triangles).

- none specifies no color, which makes nonfilled markers invisible.
- auto uses the same color as the EdgeColor property.
- flat uses the CData value of the vertex to determine the color of the maker edge.
- ColorSpec defines a single color to use for the edge (see ColorSpec for more information).

MarkerFaceColor

{none} | auto | flat | ColorSpec

Marker face color. The fill color for markers that are closed shapes (circle, square, diamond, pentagram, hexagram, and the four triangles).

- none makes the interior of the marker transparent, allowing the background to show through.
- auto uses the axes Color for the marker face color.
- flat uses the CData value of the vertex to determine the color of the face.
- ColorSpec defines a single color to use for all markers on the surfaceplot (see ColorSpec for more information).

MarkerSize

size in points

Marker size. A scalar specifying the size of the marker in points. The default value for MarkerSize is 6 points (1 point = 1/72 inch). Note that MATLAB draws the point marker (specified by the '.' symbol) at one-third the specified size.

MeshStyle

{both} | row | column

Row and column lines. This property specifies whether to draw all edge lines or just row or column edge lines.

- both draws edges for both rows and columns.
- row draws row edges only.
- column draws column edges only.

NormalMode

{auto} | manual

MATLAB generated or user-specified normal vectors. When this property is auto, MATLAB calculates vertex normals based on the coordinate data. If you specify your own vertex normals,

MATLAB sets this property to manual and does not generate its own data. See also the VertexNormals property.

Parent

handle of parent axes, hggroup, or hgtransform

Parent of this object. This property contains the handle of the object's parent. The parent is normally the axes, hggroup, or hgtransform object that contains the object.

See "Objects That Can Contain Other Objects" for more information on parenting graphics objects.

Selected

on | {off}

Is object selected? When you set this property to on, MATLAB displays selection "handles" at the corners and midpoints if the SelectionHighlight property is also on (the default). You can, for example, define the ButtonDownFcn callback to set this property to on, thereby indicating that this particular object is selected. This property is also set to on when an object is manually selected in plot edit mode.

SelectionHighlight

{on} | off

Objects are highlighted when selected. When the Selected property is on, MATLAB indicates the selected state by drawing four edge handles and four corner handles. When SelectionHighlight is off, MATLAB does not draw the handles except when in plot edit mode and objects are selected manually.

SpecularColorReflectance

scalar in the range 0 to 1

Color of specularly reflected light. When this property is 0, the color of the specularly reflected light depends on both the color of the object from which it reflects and the color of the light source.

When set to 1, the color of the specularly reflected light depends only on the color or the light source (i.e., the light object Color property). The proportions vary linearly for values in between.

SpecularExponent

scalar ≥ 1

Harshness of specular reflection. This property controls the size of the specular spot. Most materials have exponents in the range of 5 to 20.

SpecularStrength

scalar ≥ 0 and ≤ 1

Intensity of specular light. This property sets the intensity of the specular component of the light falling on the surface. Specular light comes from light objects in the axes.

You can also set the intensity of the ambient and diffuse components of the light on the surfaceplot object. See the AmbientStrength and DiffuseStrength properties. Also see the material function.

Тад

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when you are constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callbacks. You can define Tag as any string.

For example, you might create an areaseries object and set the Tag property.

t = area(Y, 'Tag', 'area1')

When you want to access objects of a given type, you can use findobj to find the object's handle. The following statement changes the FaceColor property of the object whose Tag is area1.

```
set(findobj('Tag', 'area1'), 'FaceColor', 'red')
```

Туре

string (read only)

Class of the graphics object. The class of the graphics object. For surfaceplot objects, Type is always the string 'surface'.

UIContextMenu

handle of a uicontextmenu object

Associate a context menu with this object. Assign this property the handle of a uicontextmenu object created in the object's parent figure. Use the uicontextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click over the object.

UserData

array

User-specified data. This property can be any data you want to associate with this object (including cell arrays and structures). The object does not set values for this property, but you can access it using the set and get functions.

VertexNormals

vector or matrix

Surfaceplot normal vectors. This property contains the vertex normals for the surfaceplot. MATLAB generates this data to perform lighting calculations. You can supply your own vertex normal data, even if it does not match the coordinate data. This can be useful to produce interesting lighting effects.

Visible {on} | off

Visibility of this object and its children. By default, a new object's visibility is on. This means all children of the object are visible unless the child object's Visible property is set to off. Setting an object's Visible property to off prevents the object from being displayed. However, the object still exists and you can set and query its properties.

XData

vector or matrix

X-coordinates. The *x*-position of the surfaceplot data points. If you specify a row vector, MATLAB replicates the row internally until it has the same number of columns as ZData.

XDataMode

{auto} | manual

Use automatic or user-specified x-axis values. If you specify XData (by setting the XData property or specifying the x input argument), MATLAB sets this property to manual and uses the specified values to label the x-axis.

If you set XDataMode to auto after having specified XData, MATLAB resets the *x*-axis ticks to 1:size(YData,1) or to the column indices of the ZData, overwriting any previous values for XData.

XDataSource

string (MATLAB variable)

Link XData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the XData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change XData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

YData

vector or matrix

Y-coordinates. The *y*-position of the surfaceplot data points. If you specify a row vector, MATLAB replicates the row internally until it has the same number of rows as ZData.

YDataMode

{auto} | manual

Use automatic or user-specified x-axis values. If you specify XData, MATLAB sets this property to manual.

If you set YDataMode to auto after having specified YData, MATLAB resets the *y*-axis ticks and *y*-tick labels to the row indices of the ZData, overwriting any previous values for YData.

YDataSource

string (MATLAB variable)

Link YData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the YData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change YData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

ZData

matrix

Z-coordinates. The *z*-position of the surfaceplot data points. See the Description section for more information.

ZDataSource

string (MATLAB variable)

Link ZData to MATLAB variable. Set this property to a MATLAB variable that is evaluated in the base workspace to generate the ZData.

MATLAB reevaluates this property only when you set it. Therefore, a change to workspace variables appearing in an expression does not change ZData.

You can use the refreshdata function to force an update of the object's data. refreshdata also enables you to specify that the data source variable be evaluated in the workspace of a function from which you call refreshdata.

See the refreshdata reference page for more information.

Note If you change one data source property to a variable that contains data of a different dimension, you might cause the function to generate a warning and not render the graph until you have changed all data source properties to appropriate values.

Purpose

Surface plot with colormap-based lighting



GUI Alternatives To graph selected variables, use the Plot Selector Implot(t,y) Implot(t,y) Implot and the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in *plot edit* mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.

Syntax surfl(Z)
 surfl(...,'light')
 surfl(...,s)
 surfl(X,Y,Z,s,k)
 h = surfl(...)

Description

The surfl function displays a shaded surface based on a combination of ambient, diffuse, and specular lighting models.


surfl(Z) and surfl(X,Y,Z) create three-dimensional shaded surfaces using the default direction for the light source and the default lighting coefficients for the shading model. X, Y, and Z are vectors or matrices that define the *x*, *y*, and *z* components of a surface.

surf1(..., 'light') produces a colored, lighted surface using a MATLAB light object. This produces results different from the default lighting method, surf1(..., 'cdata'), which changes the color data for the surface to be the reflectance of the surface.

surfl(...,s) specifies the direction of the light source. s is a two- or three-element vector that specifies the direction from a surface to a light source. s = [sx sy sz] or s = [azimuth elevation]. The default s is 45° counterclockwise from the current view direction.


surfl(X,Y,Z,s,k) specifies the reflectance constant. k is a four-element vector defining the relative contributions of ambient light,

	<pre>diffuse reflection, specular reflection, and the specular shine coefficient. k = [ka kd ks shine] and defaults to [.55,.6,.4,10]. h = surfl() returns a handle to a surface graphics object.</pre>
Remarks	surfl does not accept complex inputs.
	For smoother color transitions, use colormaps that have linear intensity variations (e.g., gray, copper, bone, pink).
	The ordering of points in the X, Y, and Z matrices defines the inside and outside of parametric surfaces. If you want the opposite side of the surface to reflect the light source, use $surfl(X',Y',Z')$. Because of the way surface normal vectors are computed, $surfl$ requires matrices that are at least 3-by-3.
Examples	<pre>View peaks using colormap-based lighting. [x,y] = meshgrid(-3:1/8:3); z = peaks(x,y); surfl(x,y,z); shading interp colormap(gray); axis([-3 3 -3 3 -8 8])</pre>



To plot a lighted surface from a view direction other than the default,

view([10 10])
grid on
hold on
surfl(peaks)
shading interp
colormap copper
hold off



See Also


colormap, shading, light

"Surface and Mesh Creation" on page 1-107 for functions related to surfaces $% \left({{{\rm{S}}_{{\rm{s}}}}} \right)$

"Lighting" on page 1-111 for functions related to lighting

surfnorm

Purpose	Compute and display 3-D surface normals	
Syntax	surfnorm(Z) surfnorm(X,Y,Z) [Nx,Ny,Nz] = surfnorm()	
Description	The surfnorm function computes surface normals for the surface defined by X, Y, and Z. The surface normals are unnormalized and valid at each vertex. Normals are not shown for surface elements that face away from the viewer. surfnorm does not accept complex inputs.	
	surfnorm(Z) and $surfnorm(X,Y,Z)$ plot a surface and its surface normals. Z is a matrix that defines the z component of the surface. X and Y are vectors or matrices that define the x and y components of the surface. Reverse the direction of the normals by calling surfnorm with transposed arguments:	
	<pre>surfnorm(X',Y',Z')</pre>	
	[Nx,Ny,Nz] = surfnorm() returns the components of the three-dimensional surface normals for the surface.	
	surfl uses surfnorm to compute surface normals when calculating the reflectance of a surface.	
Algorithm	The surface normals are based on a bicubic fit of the data in X , Y , and Z . For each vertex, diagonal vectors are computed and crossed to form the normal.	



See Also surf, quiver3 "Color Operations" on page 1-108 for related functions

Purpose	Singular value decomposition	
Syntax	<pre>s = svd(X) [U,S,V] = svd(X) [U,S,V] = svd(X,0) [U,S,V] = svd(X,'econ')</pre>	
Description	The svd command computes the matrix singular value decomposition.	
	s = svd(X) returns a vector of singular values.	
	[U,S,V] = svd(X) produces a diagonal matrix S of the same dimension as X, with nonnegative diagonal elements in decreasing order, and unitary matrices U and V so that X = U*S*V'.	
	[U,S,V] = svd(X,0) produces the "economy size" decomposition. If X is m-by-n with m > n, then svd computes only the first n columns of U and S is n-by-n.	
	[U,S,V] = svd(X, econ) also produces the "economy size" decomposition. If X is m-by-n with m >= n, it is equivalent to $svd(X,0)$. For m < n, only the first m columns of V are computed and S is m-by-m.	
Examples	For the matrix	
	X =	
	1 2	
	3 4 5 6	
	7 8	
	the statement	
	[U,S,V] = svd(X)	
	produces	
	U =	
	-0.1525 -0.8226 -0.3945 -0.3800	

-0.3499 -0.5474 -0.7448	-0.4214 -0.0201 0.3812	0.2428 0.6979 -0.5462	0.8007 -0.4614 0.0407
S =			
14.2691	0		
0	0.6268		
0	0		
0	0		
V =			
-0.6414	0.7672		
-0.7672	-0.6414		

The economy size decomposition generated by

[U,S,V] = svd(X,0)

produces

U =		
	-0.1525	-0.8226
	-0.3499	-0.4214
	-0.5474	-0.0201
	-0.7448	0.3812
S =		
	14.2691	0
	0	0.6268
V =		
	-0.6414	0.7672
	-0.7672	-0.6414

Algorithm svd uses the LAPACK routines listed in the following table to compute the singular value decomposition.

	Real	Complex
X double	DGESVD	ZGESVD
X single	SGESVD	CGESVD

Diagnostics If the limit of 75 QR step iterations is exhausted while seeking a singular value, this message appears:

Solution will not converge.

References [1] Anderson, E., Z. Bai, C. Bischof, S. Blackford, J. Demmel, J. Dongarra, J. Du Croz, A. Greenbaum, S. Hammarling, A. McKenney, and D. Sorensen, *LAPACK User's Guide* (http://www.netlib.org/lapack/lug/lapack_lug.html), Third Edition, SIAM, Philadelphia, 1999.

Purpose	Find singular values and vectors
Syntax	<pre>s = svds(A) s = svds(A,k) s = svds(A,k,sigma) s = svds(A,k,'L') s = svds(A,k,sigma,options) [U,S,V] = svds(A,) [U,S,V,flag] = svds(A,)</pre>
Description	<pre>s = svds(A) computes the six largest singular values and associated singular vectors of matrix A. If A is m-by-n, svds(A) manipulates eigenvalues and vectors returned by eigs(B), where B = [sparse(m,m) A; A' sparse(n,n)], to find a few singular values and vectors of A. The positive eigenvalues of the symmetric matrix B are the same as the singular values of A.</pre>
	s = svds(A,k) computes the k largest singular values and associated singular vectors of matrix A.
	s = svds(A,k,sigma) computes the k singular values closest to the scalar shift sigma. For example, $s = svds(A,k,0)$ computes the k

smallest singular values and associated singular vectors.


s = svds(A,k, L') computes the k largest singular values (the default).

s = svds(A,k,sigma,options) sets some parameters (see eigs):

Option Structure Fields and Descriptions

Field name	Parameter	Default
options.tol	<pre>Convergence tolerance: norm(AV-US,1)<=tol*norm(A,1)</pre>	1e-10
options.maxit	Maximum number of iterations	300
options.disp	Number of values displayed each iteration	0

	[U,S,V] = svds(A,) returns three output arguments, and if A is m-by-n:
	• U is m-by-k with orthonormal columns
	• S is k-by-k diagonal
	• V is n-by-k with orthonormal columns
	• $U*S*V'$ is the closest rank k approximation to A
	[U,S,V,flag] = svds(A,) returns a convergence flag. If eigs converged then norn(A*V-U*S,1) <= tol*norm(A,1) and flag is 0. If eigs did not converge, then flag is 1.
	Note svds is best used to find a few singular values of a large, sparse matrix. To find all the singular values of such a matrix, svd(full(A)) will usually perform better than svds(A,min(size(A))).
Algorithm	svds(A,k) uses eigs to find the k largest magnitude eigenvalues and corresponding eigenvectors of $B = [0 A; A' 0]$.
	svds(A,k,0) uses eigs to find the 2k smallest magnitude eigenvalues and corresponding eigenvectors of B = [0 A; A' 0], and then selects the k positive eigenvalues and their eigenvectors.
Example	west0479 is a real 479-by-479 sparse matrix. svd calculates all 479 singular values. svds picks out the largest and smallest singular values.
	<pre>load west0479 s = svd(full(west0479)) sl = svds(west0479,4) ss = svds(west0479,6,0)</pre>
	These plots show some of the singular values of west0479 as computed by svd and $svds$.



The largest singular value of west0479 can be computed a few different ways:

svds(west0479,1) =
3.189517598808622e+05
max(svd(full(west0479))) =
3.18951759880862e+05
norm(full(west0479)) =
3.189517598808623e+05

and estimated:

normest(west0479) =
 3.189385666549991e+05

See Also svd, eigs

swapbytes

Purpose	Swap byte ordering	
Syntax	Y = swapbytes(X)	
Description	Y = swapbytes(X) reverses the byte ordering of each element in array X, converting little-endian values to big-endian (and vice versa). The input array must contain all full, noncomplex, numeric elements.	
Examples	Example 1	
	Reverse the byte order for a scalar 32-bit value, changing hexadecimal 12345678 to 78563412:	
	A = uint32(hex2dec('12345678'));	
	<pre>B = dec2hex(swapbytes(A)) B = 78562412</pre>	
	78563412	
	Example 2	
	Reverse the byte order for each element of a 1-by-4 matrix:	
	X = uint16([0 1 128 65535])	
	X = 0 1 128 65535	
	Y = swapbytes(X); Y =	
	0 256 32768 65535	
	Examining the output in hexadecimal notation shows the byte swapping:	

format hex X, Y X = 0000 0001 0080 ffff

```
Y = 0000 0100 8000 ffff
```

Example 3

Create a three-dimensional array A of 16-bit integers and then swap the bytes of each element:

```
format hex
A = uint16(magic(3) * 150);
A(:,:,2) = A * 40;
А
A(:,:,1) =
   04b0
          0096
                  0384
   01c2
          02ee
                  041a
   0258
          0546
                  012c
A(:,:,2) =
   bb80
          1770
                  8ca0
   4650
          7530
                  a410
   5dc0
          d2f0
                  2ee0
swapbytes(A)
ans(:,:,1) =
   b004
          9600
                  8403
   c201
          ee02
                  1a04
   5802
          4605
                  2c01
ans(:,:,2) =
   80bb
          7017
                  a08c
   5046
          3075
                  10a4
   c05d
          f0d2
                  e02e
```

See Also typecast

switch

Purpose	Switch among several cases, based on expression	
Syntax	<pre>switch switch_expr case case_expr statement,, statement case {case_expr1, case_expr2, case_expr3,} statement,, statement otherwise statement,, statement end</pre>	

Discussion

The switch statement syntax is a means of conditionally executing code. In particular, switch executes one set of statements selected from an arbitrary number of alternatives. Each alternative is called a *case*, and consists of

- The case statement
- One or more case expressions
- One or more statements

In its basic syntax, switch executes the statements associated with the first case where switch_expr == case_expr. When the case expression is a cell array (as in the second case above), switch executes the case where any of the elements of the cell array matches the switch expression. If no case expression matches the switch expression, then control passes to the otherwise case (if it exists). After the case is executed, program execution resumes with the statement after the end.

The switch_expr can be a scalar or a string. A scalar switch_expr matches a case_expr if switch_expr==case_expr. A string switch_expr matches a case_expr if strcmp(switch_expr,case-expr) returns logical 1 (true).

A case_expr can include arithmetic or logical operators, but not relational operators such as < or >. To test for inequality, use if-elseif statements.

Note for C Programmers Unlike the C language switch construct, the MATLAB switch does not "fall through." That is, switch executes only the first matching case; subsequent matching cases do not execute. Therefore, break statements are not used. **Examples** To execute a certain block of code based on what the string, method, is set to. method = 'Bilinear'; switch lower(method) case {'linear','bilinear'} disp('Method is linear') case 'cubic' disp('Method is cubic') case 'nearest' disp('Method is nearest') otherwise disp('Unknown method.') end Method is linear See Also case, otherwise, end, if, else, elseif, while

symamd

Purpose	Symmetric approximate minimum degree permutation		
Syntax	p = symamd(S) p = symamd(S,knobs) [p,stats] = symamd()		
Description	<pre>p = symamd(S) for a symmetric positive definite matrix S, returns the permutation vector p such that S(p,p) tends to have a sparser Cholesky factor than S. To find the ordering for S, symamd constructs a matrix M such that spones(M'*M) = spones (S), and then computes p = colamd(M). The symamd function may also work well for symmetric indefinite matrices.</pre>		
	S must be square; only the strictly lower triangular part is referenced.		
	columns with r and ordered la	<pre>,knobs) where knobs is a scalar. If S is n-by-n, rows and nore than knobs*n entries are removed prior to ordering, st in the output permutation p. If the knobs parameter is en knobs = spparms('wh_frac').</pre>	
		symamd() produces the optional vector stats that about the ordering and the validity of the matrix S.	
	stats(1)	Number of dense or empty rows ignored by symamd	
	stats(2)	Number of dense or empty columns ignored by <code>symamd</code>	
	stats(3)	Number of garbage collections performed on the internal data structure used by symamd (roughly of size 8.4*nnz(tril(S,-1)) + 9n integers)	
	<pre>stats(4)</pre>	0 if the matrix is valid, or 1 if invalid	
	stats(5)	Rightmost column index that is unsorted or contains duplicate entries, or 0 if no such column exists	
	stats(6)	Last seen duplicate or out-of-order row index in the column index given by stats(5), or 0 if no such row index exists	
	stats(7)	Number of duplicate and out-of-order row indices	


Although, MATLAB built-in functions generate valid sparse matrices, a user may construct an invalid sparse matrix using the MATLAB C or Fortran APIs and pass it to symamd. For this reason, symamd verifies that S is valid:

- If a row index appears two or more times in the same column, symamd ignores the duplicate entries, continues processing, and provides information about the duplicate entries in stats(4:7).
- If row indices in a column are out of order, symamd sorts each column of its internal copy of the matrix S (but does not repair the input matrix S), continues processing, and provides information about the out-of-order entries in stats(4:7).
- If S is invalid in any other way, symamd cannot continue. It prints an error message, and returns no output arguments (p or stats).

The ordering is followed by a symmetric elimination tree post-ordering.

Examples Here is a comparison of reverse Cuthill-McKee and minimum degree on the Bucky ball example mentioned in the symrcm reference page.

```
B = bucky+4*speye(60);
r = symrcm(B);
p = symamd(B);
R = B(r,r);
S = B(p,p);
subplot(2,2,1), spy(R,4), title('B(r,r)')
subplot(2,2,2), spy(S,4), title('B(s,s)')
subplot(2,2,3), spy(chol(R),4), title('chol(B(r,r))')
subplot(2,2,4), spy(chol(S),4), title('chol(B(s,s))')
```



Even though this is a very small problem, the behavior of both orderings is typical. RCM produces a matrix with a narrow bandwidth which fills in almost completely during the Cholesky factorization. Minimum degree produces a structure with large blocks of contiguous zeros which do not fill in during the factorization. Consequently, the minimum degree ordering requires less time and storage for the factorization.

See Also colamd, colperm, spparms, symrcm, amd

References The authors of the code for symamd are Stefan I. Larimore and Timothy A. Davis (davis@cise.ufl.edu), University of Florida. The algorithm was developed in collaboration with John Gilbert,

Xerox PARC, and Esmond Ng, Oak Ridge National Laboratory. Sparse Matrix Algorithms Research at the University of Florida: http://www.cise.ufl.edu/research/sparse/

symbfact

Purpose	Symbolic factorization analysis			
Syntax	<pre>count = symbfact(A) count = symbfact(A,'sym') count = symbfact(A,'col') count = symbfact(A,'row') count = symbfact(A,'lo') [count,h,parent,post,R] = symbfact() [count,h,parent,post,L] = symbfact(A,type,'lower')</pre>			
Description	<pre>count = symbfact(A) returns the vector of row counts of R=chol(A'* symbfact should be much faster than chol(A).</pre>			
	<pre>count = symbfact(A,'sym') is the same as count = symbfact(A).</pre>			
		<pre>fact(A, 'col') returns row counts of R=chol(A'*A) ng it explicitly).</pre>		
	<pre>count = symbfact(A, 'row') returns row counts of R=chol(A*A').</pre>			
	<pre>count = symbfact(A,'lo') is the same as count = symbfact(A) and uses tril(A).</pre>			
	<pre>[count,h,parent,post,R] = symbfact() has several optional return values.</pre>			
	The flop count for a subsequent Cholesky factorization is $sum(cou)$			
	Return Value	Description		
	h	Height of the elimination tree		

value		
h	Height of the elimination tree	
parent	The elimination tree itself	
post	Postordering of the elimination tree	
R	0-1 matrix having the structure of chol(A) for the symmetric case, chol(A'*A) for the 'col' case, or chol(A*A') for the 'row' case.	

symbfact(A) and symbfact(A, 'sym') use the upper triangular part of A (triu(A)) and assume the lower triangular part is the transpose of the upper triangular part. symbfact(A, 'lo') uses tril(A) instead.

[count,h,parent,post,L] = symbfact(A,type,'lower') where type is one of 'sym','col', 'row', or'lo' returns a lower triangular symbolic factor L=R'. This form is quicker and requires less memory.

See Also chol, etree, treelayout

symmlq

Purpose	Symmetric LQ method	
Syntax	<pre>x = symmlq(A,b) symmlq(A,b,tol) symmlq(A,b,tol,maxit) symmlq(A,b,tol,maxit,M) symmlq(A,b,tol,maxit,M1,M2) symmlq(A,b,tol,maxit,M1,M2,x0) [x,flag] = symmlq(A,b,) [x,flag,relres] = symmlq(A,b,) [x,flag,relres,iter] = symmlq(A,b,) [x,flag,relres,iter,resvec] = symmlq(A,b,) [x,flag,relres,iter,resvec,resveccg] = symmlq(A,b,)</pre>	
Description	x = symmlq(A,b) attempts to solve the system of linear equations A*x=b for x. The n-by-n coefficient matrix A must be symmetric but need not be positive definite. It should also be large and sparse. The column vector b must have length n. A can be a function handle afun such that afun(x) returns A*x. See "Function Handles" in the MATLAB Programming documentation for more information.	
	"Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide additional parameters to the function afun, as well as the preconditioner function mfun described below, if necessary.	
	If symmlq converges, a message to that effect is displayed. If symmlq fails to converge after the maximum number of iterations or halts for any reason, a warning message is printed displaying the relative residual norm(b-A*x)/norm(b) and the iteration number at which the method stopped or failed.	
	<pre>symmlq(A,b,tol) specifies the tolerance of the method. If tol is [], then symmlq uses the default, 1e-6.</pre>	
	<pre>symmlq(A,b,tol,maxit) specifies the maximum number of iterations. If maxit is [], then symmlq uses the default, min(n,20).</pre>	

symmlq(A,b,tol,maxit,M) and symmlq(A,b,tol,maxit,M1,M2) use the symmetric positive definite preconditioner M or M = M1*M2 and effectively solve the system inv(sqrt(M))*A*inv(sqrt(M))*y = inv(sqrt(M))*b for y and then return x = in(sqrt(M))*y. If M is [] then symmlq applies no preconditioner. M can be a function handle mfun such that mfun(x) returns M\x.

symmlq(A,b,tol,maxit,M1,M2,x0) specifies the initial guess. If x0 is
[], then symmlq uses the default, an all-zero vector.

Flag	Convergence
0	<pre>symmlq converged to the desired tolerance tol within maxit iterations.</pre>
1	symmlq iterated maxit times but did not converge.
2	Preconditioner M was ill-conditioned.
3	<pre>symmlq stagnated. (Two consecutive iterates were the same.)</pre>
4	One of the scalar quantities calculated during symmlq became too small or too large to continue computing.
5	Preconditioner M was not symmetric positive definite.

[x,flag] = symmlq(A,b,...) also returns a convergence flag.

Whenever flag is not 0, the solution x returned is that with minimal norm residual computed over all the iterations. No messages are displayed if the flag output is specified.

[x,flag,relres] = symmlq(A,b,...) also returns the relative residual norm(b-A*x)/norm(b). If flag is 0, relres <= tol.</pre>

[x,flag,relres,iter] = symmlq(A,b,...) also returns the iteration
number at which x was computed, where 0 <= iter <= maxit.</pre>

[x,flag,relres,iter,resvec] = symmlq(A,b,...) also returns a vector of estimates of the symmlq residual norms at each iteration, including norm(b-A*x0). [x,flag,relres,iter,resvec,resveccg] = symmlq(A,b,...) also returns a vector of estimates of the conjugate gradients residual norms at each iteration.

Examples Example 1

```
n = 100;
on = ones(n,1);
A = spdiags([-2*on 4*on -2*on],-1:1,n,n);
b = sum(A,2);
tol = 1e-10;
maxit = 50; M1 = spdiags(4*on,0,n,n);
x = symmlq(A,b,tol,maxit,M1);
symmlq converged at iteration 49 to a solution with relative
residual 4.3e-015
```

Example 2

This example replaces the matrix A in Example 1 with a handle to a matrix-vector product function afun. The example is contained in an M-file run_symmlq that

- Calls symmlq with the function handle @afun as its first argument.
- Contains afun as a nested function, so that all variables in run_symmlq are available to afun.

The following shows the code for run_symmlq:

```
function x1 = run_symmlq
n = 100;
on = ones(n,1);
A = spdiags([-2*on 4*on -on],-1:1,n,n);
b = sum(A,2);
tol = 1e-8;
maxit = 15;
M1 = spdiags([on/(-2) on],-1:0,n,n);
M2 = spdiags([4*on -on],0:1,n,n);
```

```
x1 = symmlq(@afun,b,tol,maxit,M1);
    function y = afun(x)
        y = 4 * x;
        y(2:n) = y(2:n) - 2 * x(1:n-1);
        y(1:n-1) = y(1:n-1) - 2 * x(2:n);
        end
end
```

When you enter

x1=run_symmlq;

MATLAB software displays the message

```
symmlq converged at iteration 49 to a solution with relative residual 4.3e-015
```

Example 3

Use a symmetric indefinite matrix that fails with pcg.

```
A = diag([20:-1:1,-1:-1:-20]);
b = sum(A,2); % The true solution is the vector of all ones.
x = pcg(A,b); % Errors out at the first iteration.
pcg stopped at iteration 1 without converging to the desired
tolerance 1e-006 because a scalar quantity became too small or
too large to continue computing.
The iterate returned (number 0) has relative residual 1
```

However, symmlq can handle the indefinite matrix A.

x = symmlq(A,b,1e-6,40); symmlq converged at iteration 39 to a solution with relative residual 1.3e-007

See Also bicg, bicgstab, cgs, lsqr, gmres, minres, pcg, qmr

function_handle (@), mldivide (\)

References [1] Barrett, R., M. Berry, T. F. Chan, et al., *Templates for the Solution of Linear Systems: Building Blocks for Iterative Methods*, SIAM, Philadelphia, 1994.


[2] Paige, C. C. and M. A. Saunders, "Solution of Sparse Indefinite Systems of Linear Equations." *SIAM J. Numer. Anal.*, Vol.12, 1975, pp. 617-629.

Purpose	Sparse reverse Cuthill-McKee ordering
Syntax	r = symrcm(S)
Description	r = symrcm(S) returns the symmetric reverse Cuthill-McKee ordering of S. This is a permutation r such that $S(r,r)$ tends to have its nonzero elements closer to the diagonal. This is a good preordering for LU or Cholesky factorization of matrices that come from long, skinny problems. The ordering works for both symmetric and nonsymmetric S. For a real, symmetric sparse matrix, S, the eigenvalues of $S(r,r)$ are
	the same as those of S, but eig(S(r,r)) probably takes less time to compute than eig(S).
Algorithm	The algorithm first finds a pseudoperipheral vertex of the graph of the matrix. It then generates a level structure by breadth-first search and orders the vertices by decreasing distance from the pseudoperipheral vertex. The implementation is based closely on the SPARSPAK implementation described by George and Liu.
Examples	The statement
	B = bucky;
	uses an M-file in the demos toolbox to generate the adjacency graph of a truncated icosahedron. This is better known as a soccer ball, a Buckminster Fuller geodesic dome (hence the name bucky), or, more recently, as a 60-atom carbon molecule. There are 60 vertices. The vertices have been ordered by numbering half of them from one hemisphere, pentagon by pentagon; then reflecting into the other hemisphere and gluing the two halves together. With this numbering, the matrix does not have a particularly narrow bandwidth, as the first spy plot shows
	<pre>subplot(1,2,1), spy(B), title('B')</pre>
	The reverse Cuthill-McKee ordering is obtained with

p = symrcm(B); R = B(p,p);

The spy plot shows a much narrower bandwidth.

subplot(1,2,2), spy(R), title('B(p,p)')



This example is continued in the reference pages for symamd. The bandwidth can also be computed with

[i,j] = find(B); bw = max(i-j) + 1;

The bandwidths of B and R are 35 and 12, respectively.

See Also colamd, colperm, symamd

References [1] George, Alan and Joseph Liu, *Computer Solution of Large Sparse Positive Definite Systems*, Prentice-Hall, 1981.

[2] Gilbert, John R., Cleve Moler, and Robert Schreiber, "Sparse Matrices in MATLAB: Design and Implementation," *SIAM Journal on Matrix Analysis*, 1992. A slightly expanded version is also available as a technical report from the Xerox Palo Alto Research Center.

Purpose	Determine symbolic variables in expression
Syntax	symvar 'expr' s = symvar('expr')
Description	<pre>symvar 'expr' searches the expression, expr, for identifiers other than i, j, pi, inf, nan, eps, and common functions. symvar displays those variables that it finds or, if no such variable exists, displays an empty cell array, {}.</pre>
	<pre>s = symvar('expr') returns the variables in a cell array of strings, s. If no such variable exists, s is an empty cell array.</pre>
Examples	<pre>symvar finds variables beta1 and x, but skips pi and the cos function. symvar 'cos(pi*x - beta1)' ans = 'beta1'</pre>
_	' X '
See Also	findstr

synchronize

Purpose	Synchronize and resample two timeseries objects using common time vector
Syntax	<pre>[ts1 ts2] = synchronize(ts1,ts2,'SynchronizeMethod')</pre>
Description	<pre>[ts1 ts2] = synchronize(ts1,ts2,'SynchronizeMethod') creates two new timeseries objects by synchronizing ts1 and ts2 using a common time vector. The string 'SynchronizeMethod' defines the method for synchronizing the timeseries and can be one of the following:</pre>
	• 'Union' — Resample timeseries objects using a time vector that is a union of the time vectors of ts1 and ts2 on the time range where the two time vectors overlap.
	• 'Intersection' — Resample timeseries objects on a time vector that is the intersection of the time vectors of ts1 and ts2.
	• 'Uniform' — Requires an additional argument as follows:
	<pre>[ts1 ts2] = synchronize(ts1,ts2,'Uniform','Interval',value)</pre>
	This method resamples time series on a uniform time vector, where value specifies the time interval between the two samples. The uniform time vector is the overlap of the time vectors of ts1 and ts2. The interval units are assumed to be the smaller units of ts1 and ts2.
	You can specify additional arguments by using property-value pairs:
	• 'InterpMethod': Forces the specified interpolation method (over the default method) for this synchronize operation. Can be either a string, 'linear' or 'zoh', or a tsdata.interpolation object that

• 'QualityCode': Integer (between -128 and 127) used as the quality code for both time series after the synchronization.

contains a user-defined interpolation method.

• 'KeepOriginalTimes': Logical value (true or false) indicating whether the new time series should keep the original time values. For example,

```
ts1 = timeseries([1 2],[datestr(now); datestr(now+1)]);
ts2 = timeseries([1 2],[datestr(now-1); datestr(now)]);
```

Note that ts1.timeinfo.StartDate is one day after ts2.timeinfo.StartDate. If you use

[ts1 ts2] = synchronize(ts1,ts2,'union');

the ts1.timeinfo.StartDate is changed to match ts2.TimeInfo.StartDate and ts1.Time changes to 1.

But if you use

```
[ts1 ts2] =
synchronize(ts1,ts2,'union','KeepOriginalTimes',true);
```

ts1.timeinfo.StartDate is unchanged and ts1.Time is still 0.

• 'tolerance': Real number used as the tolerance for differentiating two time values when comparing the ts1 and ts2 time vectors. The default tolerance is 1e-10. For example, when the sixth time value in ts1 is 5+(1e-12) and the sixth time value in ts2 is 5-(1e-13), both values are treated as 5 by default. To differentiate those two times, you can set 'tolerance' to a smaller value such as 1e-15, for example.

See Also timeseries

syntax

Purpose	Two ways to call MATLAB	functions
---------	-------------------------	-----------

Description You can call MATLAB functions using either *command syntax* or *function syntax*, as described below.

Command Syntax

A function call in this syntax consists of the function name followed by one or more arguments separated by spaces:

functionname arg1 arg2 ... argn

Command syntax does not allow you to obtain any values that might be returned by the function. Attempting to assign output from the function to a variable using command syntax generates an error. Use function syntax instead.

Examples of command syntax:

save mydata.mat x y z import java.awt.Button java.lang.String

Arguments are treated as string literals. See the examples below, under "Argument Passing" on page 2-3899.

Function Syntax

A function call in this syntax consists of the function name followed by one or more arguments separated by commas and enclosed in parentheses:

```
functionname(arg1, arg2, ..., argn)
```

You can assign the output of the function to one or more output values. When assigning to more than one output variable, separate the variables by commas or spaces and enclose them in square brackets ([]):

```
[out1,out2,...,outn] = functionname(arg1, arg2, ..., argn)
```

Examples of function syntax:

```
copyfile('srcfile', '..\mytests', 'writable')
[x1,x2,x3,x4] = deal(A{:})
```

Arguments are passed to the function by value. See the examples below, under "Argument Passing" on page 2-3899.

Argument Passing

When calling a function using command syntax, MATLAB passes the arguments as string literals. When using function syntax, arguments are passed by value.

In the following example, assign a value to A and then call disp on the variable to display the value passed. Calling disp with command syntax passes the variable name, 'A':

while function syntax passes the value assigned to A:

```
A = pi;
disp(A)
3.1416
```

The next example passes two strings to strcmp for comparison. Calling the function with command syntax compares the variable names, 'str1' and 'str2':

```
str1 = 'one'; str2 = 'one';
strcmp str1 str2
ans =
0 (unequal)
```

while function syntax compares the values assigned to the variables, 'one' and 'one':

```
str1 = 'one'; str2 = 'one';
strcmp(str1, str2)
```

```
ans =
1 (equal)
```

Passing Strings

When using the function syntax to pass a string literal to a function, you must enclose the string in single quotes, ('string'). For example, to create a new folder called myapptests, use

```
mkdir('myapptests')
```

On the other hand, variables that contain strings do not need to be enclosed in quotes:

```
folder = 'myapptests';
mkdir(folder)
```

See Also "Checking for Coding Problems", mlint

Purpose	Execute operating system command and return result
Syntax	system('command') [status, result] = system('command') [status,result] = system('command',' -echo ')

Description system ('command') calls upon the operating system to run the specified command, for example dir or 1s or a UNIX¹⁷ shell script, and directs the output to the MATLAB software. The command executes in a system shell, not in the shell that you used to launch MATLAB. If command runs successfully, ans is 0. If command fails or does not exist on your operating system, ans is a nonzero value and an explanatory message appears.

[status, result] = system('command') calls upon the operating system to run command, and directs the output to MATLAB. If command runs successfully, status is 0 and result contains the output from command. If command fails or does not exist on your operating system, status is a nonzero value and result contains an explanatory message.

[status,result] = system('command','-echo') forces the output to the Command Window, even though it is also being assigned into a variable.

This function is interchangeable with the dos and unix functions. They all have the same effect.

Note Running system on a Microsoft Windows platform with a command that relies on the current folder fails when the current folder is specified using a UNC pathname because DOS does not support UNC pathnames. When this happens, MATLAB returns the error:

??? Error using ==> system DOS commands may not be executed when the current directory is a UNC pathname.

To work around this limitation, change the folder to a mapped drive prior to running system or a function that calls system.

Examples On a Windows system, display the current folder by accessing the operating system.

17. UNIX is a registered trademark of The Open Group in the United States and other countries.

```
[status currdir] = system('cd')
status =
0
currdir =
D:\work\matlab\test
See Also
! (exclamation point), computer, dos, perl, unix, winopen
"Running External Programs" in the MATLAB Desktop Tools and
Development Environment documentation
```

Purpose	Tangent of argument in radians
Syntax	Y = tan(X)
Description	The tan function operates element-wise on arrays. The function's domains and ranges include complex values. All angles are in radians. Y = tan(X) returns the circular tangent of each element of X.
Examples	Graph the tangent function over the domain $-\pi/2 < x < \pi/2$. x = (-pi/2)+0.01:0.01:(pi/2)-0.01; plot(x,tan(x)), grid on
	80
	40
	0
	-40
	-60 -80
	-100 - 1.5 - 1 - 0.5 = 0.5 = 1.5 - 1.5 = 0.5 The expression tan(pi/2) does not evaluate as infinite but as

The expression $\tan(pi/2)$ does not evaluate as infinite but as the reciprocal of the floating point accuracy eps since pi is only a floating-point approximation to the exact value of π .

Definition

The tangent can be defined as

$$\tan(z) = \frac{\sin(z)}{\cos(z)}$$

Algorithm tan uses FDLIBM, which was developed at SunSoft, a Sun Microsystems, Inc. business, by Kwok C. Ng, and others. For information about FDLIBM, see http://www.netlib.org.

See Also tand, tanh, atan, atan2, atand, atanh

tand

Purpose	Tangent of argument in degrees
Syntax	Y = tand(X)
Description	Y = tand(X) is the tangent of the elements of X, expressed in degrees. For odd integers n, tand(n*90) is infinite, whereas tan(n*pi/2) is large but finite, reflecting the accuracy of the floating point value of pi.
See Also	tan, tanh, atan, atan2, atand, atanh

Purpose	Hyperbolic tangent
Syntax	Y = tanh(X)
Description	The tanh function operates element-wise on arrays. The function's domains and ranges include complex values. All angles are in radians. Y = tanh(X) returns the hyperbolic tangent of each element of X.
Examples	Graph the hyperbolic tangent function over the domain $-5 \le x \le 5$. x = -5:0.01:5; plot(x,tanh(x)), grid on 1 = 1 = 1
	-0.4 -0.6
	-0.8 -1_5 0 5
Definition	The hyperbolic tangent can be defined as

 $\tanh(z) = \frac{\sinh(z)}{\cosh(z)}$

Algorithm	tanh uses FDLIBM, which was developed at SunSoft, a Sun Microsystems, Inc. business, by Kwok C. Ng, and others. For information about FDLIBM, see http://www.netlib.org.
See Also	atan, atan2, tan

Purpose	Compress files into tar file
Syntax	tar(tarfilename,files) tar(tarfilename,files,rootfolder) entrynames = tar()
Description	tar(<i>tarfilename</i> , <i>files</i>) creates a tar file named <i>tarfilename</i> from the list of files and folders specified in <i>files</i> . Folders recursively include all of their content. If <i>files</i> includes relative paths, the tar file also contains relative paths. The tar file does not include absolute paths.
	tar(<i>tarfilename</i> , <i>files</i> , <i>rootfolder</i>) specifies the path for <i>files</i> relative to <i>rootfolder</i> rather than the current folder. Relative paths in the tar file reflect the relative paths in <i>files</i> , and do not include path information from <i>rootfolder</i> .
	entrynames = tar() returns a string cell array of the names of the files contained in <i>tarfilename</i> . If <i>files</i> includes relative paths, entrynames also contains relative paths.
Tips	tar cannot compress folders larger than 2 GB.
Input	tarfilename
Arguments	String specifying the name of the tar file. If <i>tarfilename</i> has no extension, MATLAB appends the .tar extension. The <i>tarfilename</i> extension can end in .tgz or .gz. In this case, <i>tarfilename</i> is gzipped.
	files
	String or cell array of strings containing the list of files or folders included in <i>tarfilename</i> .
	Individual files that are on the MATLAB path can be specified as partial path names. Otherwise an individual file can be specified relative to the current folder or with an absolute path.
	Folders must be specified relative to the current folder or with absolute paths. On UNIX systems, folders can also start with ~/

	or ~ <i>username</i> /, which expands to the current user's home folder or the specified user's home folder, respectively. The wildcard character * can be used when specifying files or folders, except when relying on the MATLAB path to resolve a file name or partial path name.
	rootfolder
	String specifying the path for <i>files</i> .
Example	Tar all files in the current folder to the file backup.tgz.
	<pre>tar('backup.tgz','.');</pre>
See Also	gzip gunzip untar unzip zip

Purpose	Name of system's temporary folder
Syntax	<pre>tmp_folder = tempdir</pre>
Description	<pre>tmp_folder = tempdir returns the name of the system's temporary folder, if one exists. This function does not create a new folder.</pre>
See Also	delete, recycle, tempname "Creating Temporary Files"


tempname

Purpose	Unique name for temporary file	
Syntax	tmp_nam = tempname	
Description	<pre>tmp_nam = tempname returns a unique string, tmp_nam, suitable for use as a temporary filename.</pre>	
	Note The filename that tempname generates is not guaranteed to be unique; however, it is likely to be so.	
See Also	tempdir	
	"Creating Temporary Files"	

tetramesh

Purpose	Tetrahedron mesh plot	
Syntax	tetramesh(T,X,c) tetramesh(T,X) tetramesh(TR) h = tetramesh() tetramesh(,'param','value','param','value')	
Description	tetramesh(T,X,c) displays the tetrahedrons defined in the m-by-4 matrix T as mesh. T is usually the output of a Delaunay triangulation of a 3-D set of points. A row of T contains indices into X of the vertices of a tetrahedron. X is an n-by-3 matrix, representing n points in 3 dimension. The tetrahedron colors are defined by the vector C, which is used as indices into the current colormap.	
	<pre>tetramesh(T,X) uses C = 1:m as the color for the m tetrahedra. Each tetrahedron has a different color (modulo the number of colors available in the current colormap).</pre>	
	tetramesh(TR) displays the tetrahedra in a Triangulation representation.	
	<pre>h = tetramesh() returns a vector of tetrahedron handles. Each element of h is a handle to the set of patches forming one tetrahedron. You can use these handles to view a particular tetrahedron by turning the patch 'Visible' property 'on' or 'off'.</pre>	
	tetramesh(, 'param', 'value', 'param', 'value') allows additional patch property name/property value pairs to be used when displaying the tetrahedrons. For example, the default transparency parameter is set to 0.9. You can overwrite this value by using the property name/property value pair ('FaceAlpha', value) where value is a number between 0 and 1. See Patch Properties for information about the available properties.	
Examples	<pre>Generate a 3-D Delaunay tessellation, then use tetramesh to visualize the tetrahedrons that form the corresponding simplex. d = [-1 1];</pre>	

```
[x,y,z] = meshgrid(d,d,d); % A cube
x = [x(:);0];
y = [y(:);0];
z = [z(:);0];
% [x,y,z] are corners of a cube plus the center.
dt = DelaunayTri(x,y,z);
Tes = dt(:,:);
X = [x(:) y(:) z(:)];
tetramesh(Tes,X);
camorbit(20,0)
```



You can also plot the Delaunay triangulation directly.


tetramesh

close(gcf); tetramesh(dt);

See Also trimesh, trisurf, patch, delaunayn, TriRep, TriRep.freeBoundary

texlabel

Purpose	Produce TeX format from character string	
Syntax	texlabel(f) texlabel(f,'literal')	
Description	texlabel(f) converts the MATLAB expression f into the TeX equivalent for use in text strings. It processes Greek variable names (e.g., lambda, delta, etc.) into a string that is displayed as actual Greek letters.	
	texlabel(f, 'literal') prints Greek variable names as literals.	
	If the string is too long to fit into a figure window, then the center of the expression is replaced with a tilde ellipsis (~~~).	
Examples	You can use texlabel as an argument to the title, xlabel, ylabel, zlabel, and text commands. For example,	
	<pre>title(texlabel('sin(sqrt(x^2 + y^2))/sqrt(x^2 + y^2)'))</pre>	
	By default, texlabel translates Greek variable names to the equivalent Greek letter. You can select literal interpretation by including the literal argument. For example, compare these two commands.	
	text(.5,.5, texlabel('lambda12^(3/2)/pi - pi*delta^(2/3)')) text(.25,.25, texlabel('lambda12^(3/2)/pi - pi*delta^(2/3)','literal'))	



"Annotating Plots" on page 1-97 for related functions

Purpose	Create text object in current axes	
Syntax	<pre>text(x,y,'string') text(x,y,z,'string') text(x,y,z,'string','PropertyName',PropertyValue) text('PropertyName',PropertyValue) h = text()</pre>	
Properties	For a list of properties, see Text Properties.	
Description	text is the low-level function for creating text graphics objects. Use text to place character strings at specified locations.	
	text(x,y, 'string') adds the string in quotes to the location specified by the point (x,y) x and y must be numbers of class double.	
	text(x,y,z, 'string') adds the string in 3-D coordinates. x, y and z must be numbers of class double.	
	text(x,y,z,'string',' <i>PropertyName</i> ', PropertyValue) adds the string in quotes to the location defined by the coordinates and uses the values for the specified text properties. For a description of the properties, see Text Properties.	
	text(' <i>PropertyName</i> ', PropertyValue) omits the coordinates entirely and specifies all properties using property name/property value pairs.	
	<pre>h = text() returns a column vector of handles to text objects, one handle per object. All forms of the text function optionally return this output argument.</pre>	
	See the String property for a list of symbols, including Greek letters.	
Remarks	Position Text Within the Axes	
	The default text units are the units used to plot data in the graph. Specify the text location coordinates (the x, y, and z arguments) in the data units of the current graph (see "Examples" on page 2-3920.	

You can use other units to position the text by setting the text Units

property to normalized or one of the nonrelative units (pixels, inches, centimeters, points, or characters).

Note that the Axes Units property controls the positioning of the Axes within the figure and is not related to the axes data units used for graphing.

The Extent, VerticalAlignment, and HorizontalAlignment properties control the positioning of the character string with regard to the text location point.

If the coordinates are vectors, text writes the string at all locations defined by the list of points. If the character string is an array the same length as x, y, and z, text writes the corresponding row of the string array at each point specified.

Multiline Text

When specifying strings for multiple text objects, the string can be

- A cell array of strings
- A padded string matrix

Each element of the specified string array creates a different text object.

When specifying the string for a single text object, cell arrays of strings and padded string matrices result in a text object with a multiline string, while vertical slash characters are not interpreted as separators and result in a single line string containing vertical slashes.

Behavior of the Text Function

text is a low-level function that accepts property name/property value pairs as input arguments. However, the convenience form,

```
text(x,y,z,'string')
```

is equivalent to

```
text('Position',[x,y,z],'String','string')
```


You can specify other properties only as property name/property value pairs. For a description of each property, see Text Properties. You can specify properties as property name/property value pairs, structure arrays, and cell arrays (see the set and get reference pages for examples of how to specify these data types).

text does not respect the setting of the figure or axes NextPlot property. This allows you to add text objects to an existing axes without setting hold to on.

Examples The statements

plot(0:pi/20:2*pi,sin(0:pi/20:2*pi))
text(pi,0,' \leftarrow sin(\pi)','FontSize',18)

annotate the point at (pi, 0) with the string $sin(\pi)$



The statement

text(x,y,'\ite^{i\omega\tau} = cos(\omega\tau) + i sin(\omega\tau)')

uses embedded TeX sequences to produce

$$e^{i\omega\tau} = \cos(\omega\tau) + i\sin(\omega\tau)$$

Setting Default Properties

You can set default text properties on the axes, figure, and root object levels:

set(0, 'DefaulttextProperty', PropertyValue...)
set(gcf, 'DefaulttextProperty', PropertyValue...)

set(gca, 'DefaulttextProperty', PropertyValue...)Where Property is the name of the text property and PropertyValue is
the value you are specifying. Use set and get to access text properties.See Alsoannotation, gtext, int2str, num2str, strings, title, xlabel,
ylabel, zlabel
Text Properties for property descriptions
"Object Creation" on page 1-104 for related functions

Text Properties

Purpose	Text properties	
Creating Text Objects	Use text to create text objects.	
Modifying Properties	You can set and query graphics object properties using the property editor or the set and get commands.	
	• The Property Editor is an interactive tool that enables you to see and change object property values.	
	• The set and get commands enable you to set and query the values of properties.	
	To change the default values of properties, see Setting Default Property Values.	
	See Core Objects for general information about this type of object.	
Text Property	This section lists property names along with the types of values each accepts. Curly braces {} enclose default values.	
Descriptions	Annotation hg.Annotation object Read Only	
	Control the display of text objects in legends. The Annotation property enables you to specify whether this text object is represented in a figure legend.	
	Querying the Annotation property returns the handle of an hg.Annotation object. The hg.Annotation object has a property called LegendInformation, which contains an hg.LegendEntry object.	

Once you have obtained the hg.LegendEntry object, you can set its IconDisplayStyle property to control whether the text object is displayed in a figure legend:

IconDisplayStyle Value	Purpose
on	Represent this text object in a legend (default)
off	Do not include this text object in a legend
children	Same as on because text objects do not have children

Setting the IconDisplayStyle property

These commands set the IconDisplayStyle of a graphics object with handle hobj to off:

```
hAnnotation = get(hobj, 'Annotation');
hLegendEntry = get(hAnnotation', 'LegendInformation');
set(hLegendEntry, 'IconDisplayStyle', 'off')
```

Using the IconDisplayStyle property


See "Controlling Legends" for more information and examples.

```
BackgroundColor
```

ColorSpec | {none}

Color of text extent rectangle. This property enables you to define a color for the rectangle that encloses the text Extent plus the text Margin. For example, the following code creates a text object that labels a plot and sets the background color to light green.

```
text(3*pi/4,sin(3*pi/4),...
['sin(3*pi/4) = ',num2str(sin(3*pi/4))],...
'HorizontalAlignment','center',...
```



For additional features, see the following properties:

- EdgeColor Color of the rectangle's edge (none by default).
- LineStyle Style of the rectangle's edge line (first set EdgeColor)
- LineWidth Width of the rectangle's edge line (first set EdgeColor)
- Margin Increase the size of the rectangle by adding a margin to the existing text extent rectangle. This margin is added to the text extent rectangle to define the text background area that is enclosed by the EdgeColor rectangle. Note that the text extent does not change when you change the margin; only the rectangle displayed when you set the EdgeColor property and the area defined by the BackgroundColor change.

See also Drawing Text in a Box in the MATLAB Graphics documentation for an example using background color with contour labels. BeingDeleted
 on | {off} read only

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB software sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property) It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions may not need to perform actions on objects that are going to be deleted, and therefore can check the object's BeingDeleted property before acting.

```
BusyAction
```

cancel | {queue}

Callback routine interruption. The BusyAction property enables you to control how MATLAB handles events that potentially interrupt executing callback routines. If there is a callback routine executing, callback routines invoked subsequently always attempt to interrupt it. If the Interruptible property of the object whose callback is executing is set to on (the default), then interruption occurs at the next point where the event queue is processed. If the Interruptible property is set to off, the BusyAction property (of the object owning the executing callback) determines how MATLAB handles the event. The choices are

- cancel Discard the event that attempted to execute a second callback routine.
- queue Queue the event that attempted to execute a second callback routine until the current callback finishes.

ButtonDownFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Button press callback function. A callback function that executes whenever you press a mouse button while the pointer is over the text object.

See the figure's SelectionType property to determine if modifier keys were also pressed.

Set this property to a function handle that references the callback. The function must define at least two input arguments (handle of object associated with the button down event and an event structure, which is empty for this property). For example, the following function takes different action depending on what type of selection was made:

```
function button down(src,evnt)
% src - the object that is the source of the event
% evnt - empty for this property
   sel typ = get(gcbf, 'SelectionType')
   switch sel typ
      case 'normal'
         disp('User clicked left-mouse button')
         set(src,'Selected','on')
      case 'extend'
         disp('User did a shift-click')
         set(src,'Selected','on')
      case 'alt'
         disp('User did a control-click')
         set(src,'Selected','on')
         set(src,'SelectionHighlight','off')
   end
end
```

Suppose h is the handle of a text object and that the button_down function is on your MATLAB path. The following statement assigns the function above to the ButtonDownFcn:

set(h, 'ButtonDownFcn',@button_down)

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

Children

matrix (read only)

The empty matrix; text objects have no children.

Clipping

on | {off}

Clipping mode. When Clipping is on, MATLAB does not display any portion of the text that is outside the axes.

Color

ColorSpec

Text color. A three-element RGB vector or one of the predefined names, specifying the text color. The default value is black. See ColorSpec for more information on specifying color.

CreateFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Callback function executed during object creation. A callback function that executes when MATLAB creates a text object. You must define this property as a default value for text or in a call to the text function that creates a new text object. For example, the statement

set(0, 'DefaultTextCreateFcn',@text_create)

defines a default value on the root level that sets the figure Pointer property to crosshairs whenever you create a text object. The callback function must be on your MATLAB path when you execute the above statement.

```
function text_create(src,evnt)
% src - the object that is the source of the event
% evnt - empty for this property
set(gcbf,'Pointer','crosshair')
end
```

MATLAB executes this function after setting all text properties. Setting this property on an existing text object has no effect. The function must define at least two input arguments (handle of object created and an event structure, which is empty for this property).

The handle of the object whose CreateFcn is being executed is passed by MATLAB as the first argument to the callback function and is also accessible through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

DeleteFcn

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Delete text callback function. A callback function that executes when you delete the text object (for example, when you issue a delete command or clear the axes cla or figure clf). For example, the following function displays object property data before the object is deleted.

function delete_fcn(src,evnt)
% src - the object that is the source of the event
% evnt - empty for this property

```
obj_tp = get(src,'Type');
disp([obj_tp, ' object deleted'])
disp('Its user data is:')
disp(get(src,'UserData'))
end
```

MATLAB executes the function before deleting the object's properties so these values are available to the callback function. The function must define at least two input arguments (handle of object being deleted and an event structure, which is empty for this property)

The handle of the object whose DeleteFcn is being executed is passed by MATLAB as the first argument to the callback function and is also accessible through the root CallbackObject property, which you can query using gcbo.

See Function Handle Callbacks for information on how to use function handles to define the callback function.

DisplayName

string (default is empty string)

String used by legend for this text object. The legend function uses the string defined by the DisplayName property to label this text object in the legend.

- If you specify string arguments with the legend function, DisplayName is set to this text object's corresponding string and that string is used for the legend.
- If DisplayName is empty, legend creates a string of the form, ['data' n], where n is the number assigned to the object based on its location in the list of legend entries. However, legend does not set DisplayName to this string.
- If you edit the string directly in an existing legend, DisplayName is set to the edited string.


- If you specify a string for the DisplayName property and create the legend using the figure toolbar, then MATLAB uses the string defined by DisplayName.
- To add programmatically a legend that uses the DisplayName string, call legend with the toggle or show option.

See "Controlling Legends" for more examples.

```
EdgeColor
```

ColorSpec | {none}

Color of edge drawn around text extent rectangle plus margin. This property enables you to specify the color of a box drawn around the text Extent plus the text Margin. For example, the following code draws a red rectangle around text that labels a plot.



For additional features, see the following properties:

- BackgroundColor Color of the rectangle's interior (none by default)
- LineStyle Style of the rectangle's edge line (first set EdgeColor)
- LineWidth Width of the rectangle's edge line (first set EdgeColor)
- Margin Increases the size of the rectangle by adding a margin to the area defined by the text extent rectangle. This margin is added to the text extent rectangle to define the text background area that is enclosed by the EdgeColor rectangle. Note that the text extent does not change when you change the margin; only the rectangle displayed when you set the EdgeColor property and the area defined by the BackgroundColor change.

```
Editing
```

on | {off}

Enable or disable editing mode. When this property is set to the default off, you cannot edit the text string interactively (i.e., you must change the String property to change the text). When this property is set to on, MATLAB places an insert cursor at the end of the text string and enables editing. To apply the new text string,

- 1 Press the Esc key.
- 2 Click in any figure window (including the current figure).
- **3** Reset the Editing property to off.

MATLAB then updates the String property to contain the new text and resets the Editing property to off. You must reset the Editing property to on to resume editing.

EraseMode

{normal} | none | xor | background

Erase mode. This property controls the technique MATLAB uses to draw and erase text objects. Alternative erase modes are useful for creating animated sequences where controlling the way individual objects are redrawn is necessary to improve performance and obtain the desired effect.

- normal Redraw the affected region of the display, performing the three-dimensional analysis necessary to ensure that all objects are rendered correctly. This mode produces the most accurate picture, but is the slowest. The other modes are faster, but do not perform a complete redraw and are therefore less accurate.
- none Do not erase the text when it is moved or destroyed. While the object is still visible on the screen after erasing with EraseMode none, you cannot print it because MATLAB stores no information about its former location.
- xor Draw and erase the text by performing an exclusive OR (XOR) with each pixel index of the screen beneath it. When the text is erased, it does not damage the objects beneath it. However, when text is drawn in xor mode, its color depends on the color of the screen beneath it. It is correctly colored only when it is over axes background Color, or the figure background Color if the axes Color is set to none.
- background Erase the text by drawing it in the axes background Color, or the figure background Color if the axes Color is set to none. This damages objects that are behind the erased text, but text is always properly colored.

Printing with Nonnormal Erase Modes

MATLAB always prints figures as if the EraseMode of all objects is set to normal. This means graphics objects created with EraseMode set to none, xor, or background can look differently on screen than on paper. On screen, MATLAB may mathematically combine layers of colors (for example, performing an XOR of a pixel color with that of the pixel behind it) and ignore three-dimensional sorting to obtain greater rendering speed. However, these techniques are not applied to the printed output.

You can use the MATLAB getframe command or other screen capture application to create an image of a figure containing nonnormal mode objects.

Extent

position rectangle (read only)

Position and size of text. A four-element read-only vector that defines the size and position of the text string

[left,bottom,width,height]

If the Units property is set to data (the default), left and bottom are the *x*- and *y*-coordinates of the lower left corner of the text Extent.

For all other values of Units, left and bottom are the distance from the lower left corner of the axes position rectangle to the lower left corner of the text Extent. width and height are the dimensions of the Extent rectangle. All measurements are in units specified by the Units property.

FontAngle

{normal} | italic | oblique

Character slant. MATLAB uses this property to select a font from those available on your particular system. Generally, setting this property to *italic* or *oblique* selects a slanted font.

FontName

A name, such as Courier, or the string FixedWidth

Font family. A string specifying the name of the font to use for the text object. To display and print properly, this must be a font that your system supports. The default font is Helvetica.

Specifying a Fixed-Width Font

If you want text to use a fixed-width font that looks good in any locale, you should set FontName to the string FixedWidth:

```
set(text_handle,'FontName','FixedWidth')
```

This eliminates the need to hard-code the name of a fixed-width font, which may not display text properly on systems that do not use ASCII character encoding (such as in Japan where multibyte character sets are used). A properly written MATLAB application that needs to use a fixed-width font should set FontName to FixedWidth (note that this string is case sensitive) and rely on FixedWidthFontName to be set correctly in the end user's environment.

End users can adapt a MATLAB application to different locales or personal environments by setting the root FixedWidthFontName property to the appropriate value for that locale from startup.m.

Note that setting the root FixedWidthFontName property causes an immediate update of the display to use the new font.

FontSize

 size in FontUnits

Font size. A value specifying the font size to use for text in units determined by the FontUnits property. The default point size is 10 (1 point = 1/72 inch).

FontWeight

light | {normal} | demi | bold

Weight of text characters. MATLAB uses this property to select a font from those available on your particular system. Generally, setting this property to bold or demi causes MATLAB to use a bold font.

FontUnits

{points} | normalized | inches |
centimeters | pixels

Font size units. MATLAB uses this property to determine the units used by the FontSize property. Normalized units interpret FontSize as a fraction of the height of the parent axes. When you resize the axes, MATLAB modifies the screen FontSize accordingly. pixels, inches, centimeters, and points are absolute units (1 point = 1/72 inch).

Note that if you are setting both the FontSize and the FontUnits in one function call, you must set the FontUnits property first so that MATLAB can correctly interpret the specified FontSize.

HandleVisibility

{on} | callback | off

Control access to object's handle by command-line users and GUIs. This property determines when an object's handle is visible in its parent's list of children. HandleVisibility is useful for preventing command-line users from accidentally drawing into or deleting a figure that contains only user interface devices (such as a dialog box).

Handles are always visible when HandleVisibility is set to on.

Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.

Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function. When a handle is not visible in its parent's list of children, it cannot be returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close.

When a handle's visibility is restricted using callback or off,

- The object's handle does not appear in its parent's Children property.
- Figures do not appear in the root's CurrentFigure property.
- Objects do not appear in the root's CallbackObject property or in the figure's CurrentObject property.
- Axes do not appear in their parent's CurrentAxes property.

You can set the root ShowHiddenHandles property to on to make all handles visible regardless of their HandleVisibility settings (this does not affect the values of the HandleVisibility properties).

Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

HitTest

{on} | off

Selectable by mouse click. HitTest determines if the text can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click on the text. If HitTest is set to off, clicking the text selects the object below it (which is usually the axes containing it).

For example, suppose you define the button down function of an image (see the ButtonDownFcn property) to display text at the location you click with the mouse.

First define the callback routine.

```
function bd_function
pt = get(gca, 'CurrentPoint');
text(pt(1,1),pt(1,2),pt(1,3),...
'{\fontsize{20}\oplus} The spot to label',...
'HitTest','off')
```

Now display an image, setting its ${\tt ButtonDownFcn}$ property to the callback routine.

```
load earth
image(X,'ButtonDownFcn','bd_function'); colormap(map)
```

When you click the image, MATLAB displays the text string at that location. With HitTest set to off, existing text cannot intercept any subsequent button down events that occur over the text. This enables the image's button down function to execute.

HorizontalAlignment

{left} | center | right

Horizontal alignment of text. This property specifies the horizontal justification of the text string. It determines where MATLAB places the string with regard to the point specified by the Position property. The following picture illustrates the alignment options.

HorizontalAlignment viewed with the VerticalAlignment set to middle (the default).



See the $\ensuremath{\mathsf{Extent}}$ property for related information.

```
Interpreter
    latex | {tex} | none
```


Interpret $T_{\rm E}X$ instructions. This property controls whether MATLAB interprets certain characters in the String property as $T_{\rm E}X$ instructions (default) or displays all characters literally. The options are:

- latex Supports a basic subset of the $L_{A}T_{E}X$ markup language.
- tex Supports a subset of plain $T_E X$ markup language. See the String property for a list of supported $T_E X$ instructions.
- none Displays literal characters.

Latex Interpreter

To enable the LaT_EX interpreter for text objects, set the Interpreter property to latex. For example, the following statement displays an equation in a figure at the point [.5.5], and enlarges the font to 16 points.

```
text('Interpreter','latex',...
'String','$$\int_0^x\!\int_y dF(u,v)$$',...
'Position',[.5 .5],...
'FontSize',16)
```



Information About Using TEX

The following references may be useful to people who are not familiar with $T_E X$.

- Donald E. Knuth, *The* $T_{\rm E}Xbook$, Addison Wesley, 1986.
- The T_EX Users Group home page: http://www.tug.org

```
Interruptible
    {on} | off
```

Callback routine interruption mode. The Interruptible property controls whether a text callback routine can be interrupted by subsequently invoked callback routines. Text objects have three properties that define callback routines: ButtonDownFcn, CreateFcn, and DeleteFcn. See the BusyAction property for information on how MATLAB executes callback routines.


LineStyle

{-} | -- | : | -. | none

Edge line type. This property determines the line style used to draw the edges of the text Extent. The available line styles are shown in the following table.

Symbol	Line Style
-	Solid line (default)
	Dashed line
:	Dotted line
	Dash-dot line
none	No line

For example, the following code draws a red rectangle with a dotted line style around text that labels a plot.



For additional features, see the following properties:


- BackgroundColor Color of the rectangle's interior (none by default)
- EdgeColor Color of the rectangle's edge (none by default)
- LineWidth Width of the rectangle's edge line (first set EdgeColor)
- Margin Increases the size of the rectangle by adding a margin to the existing text extent rectangle. This margin is added to the text extent rectangle to define the text background area that is enclosed by the EdgeColor rectangle. Note that the text extent does not change when you change the margin; only the rectangle displayed when you set the EdgeColor property and the area defined by the BackgroundColor change.

LineWidth

scalar (points)

Width of line used to draw text extent rectangle. When you set the text EdgeColor property to a color (the default is none), MATLAB

displays a rectangle around the text Extent. Use the LineWidth property to specify the width of the rectangle edge. For example, the following code draws a red rectangle around text that labels a plot and specifies a line width of 3 points:



For additional features, see the following properties:


- BackgroundColor Color of the rectangle's interior (none by default)
- EdgeColor Color of the rectangle's edge (none by default)
- LineStyle Style of the rectangle's edge line (first set EdgeColor)
- Margin Increases the size of the rectangle by adding a margin to the existing text extent rectangle. This margin is added to the text extent rectangle to define the text background

area that is enclosed by the EdgeColor rectangle. Note that the text extent does not change when you change the margin; only the rectangle displayed when you set the EdgeColor property and the area defined by the BackgroundColor change.

Margin

scalar (pixels)

Distance between the text extent and the rectangle edge. When you specify a color for the BackgroundColor or EdgeColor text properties, MATLAB draws a rectangle around the area defined by the text Extent plus the value specified by the Margin. For example, the following code displays a light green rectangle with a 10-pixel margin.



For additional features, see the following properties:

- BackgroundColor Color of the rectangle's interior (none by default)
- EdgeColor Color of the rectangle's edge (none by default)
- LineStyle Style of the rectangle's edge line (first set EdgeColor)
- LineWidth Width of the rectangle's edge line (first set EdgeColor)

See how margin affects text extent properties

This example enables you to change the values of the Margin property and observe the effects on the BackgroundColor area and the EdgeColor rectangle.

Click to view in editor — This link opens the MATLAB editor with the following example.

Click to run example — Use your scroll wheel to vary the Margin.

Parent

handle of axes, hggroup, or hgtransform

Parent of text object. This property contains the handle of the text object's parent. The parent of a text object is the axes, hggroup, or hgtransform object that contains it.

See Objects That Can Contain Other Objects for more information on parenting graphics objects.

Position

[x,y,[z]]

Location of text. A two- or three-element vector, [x y [z]], that specifies the location of the text in three dimensions. If you

omit the z value, it defaults to 0. All measurements are in units specified by the Units property. Initial value is [0 0 0].

Rotation

scalar (default = 0)

Text orientation. This property determines the orientation of the text string. Specify values of rotation in degrees (positive angles cause counterclockwise rotation).

Selected

on | {off}

Is object selected? When this property is set to on, MATLAB displays selection handles if the SelectionHighlight property is also set to on. You can, for example, define the ButtonDownFcn to set this property, allowing users to select the object with the mouse.

SelectionHighlight

{on} | off

Objects are highlighted when selected. When the Selected property is set to on, MATLAB indicates the selected state by drawing four edge handles and four corner handles. When SelectionHighlight is set to off, MATLAB does not draw the handles.

String

string

The text string. Specify this property as a quoted string for single-line strings, or as a cell array of strings, or a padded string matrix for multiline strings. MATLAB displays this string at the specified location. Vertical slash characters are not interpreted as line breaks in text strings, and are drawn as part of the text string. See Mathematical Symbols, Greek Letters, and TeX Characters for an example.

Note The words default, factory, and remove are reserved words that will not appear in a figure when quoted as a normal string. In order to display any of these words individually, type '\reserved_word' instead of 'reserved_word'.

When the text Interpreter property is set to Tex (the default), you can use a subset of TeX commands embedded in the string to produce special characters such as Greek letters and mathematical symbols. The following table lists these characters and the character sequences used to define them.

Character Sequence	Symbol	Character Sequence	Symbol	Character Sequence	Symbol
\alpha	α	\upsilon	υ	\sim	~
\beta	в	\phi	Φ	\leq	\leq
\gamma	Y	\chi	Х	\infty	∞
\delta	δ	\psi	Ψ	\clubsuit	*
\epsilon	ε	\omega	ω	\diamondsuit	•
\zeta	ζ	\Gamma	Г	\heartsuit	•
\eta \theta	η Θ	\Delta \Theta	$\Delta \\ \Theta$	\spadesuit \leftrightarrow	▲ ↔
\vartheta		\Lambda	Λ	\leftarrow	←
\iota	ι	\Xi	Ξ	\uparrow	\uparrow
\kappa	К	\Pi	П	\rightarrow	\rightarrow
\lambda	λ	\Sigma	Σ	\downarrow	\downarrow
\mu	μ	\Upsilon		\circ	0

Character Sequence	Symbol	Character Sequence	Symbol	Character Sequence	Symbol
\nu	V	∖Phi	Φ	\pm	±
\xi	ξ	\Psi	Ψ	\geq	2
\pi	П	\Omega	Ω	\propto	×
\rho	ρ	\forall	\forall	\partial	∂
\sigma	σ	\exists	Э	\bullet	•
\varsigma	S	\ni	Э	\div	÷
\tau	τ	\cong	\cong	\neq	≠
\equiv	≡	\approx	≈	\aleph	
\Im	I	\Re	R	\wp	ß
\otimes	\otimes	\oplus	\oplus	\oslash	Ø
\cap	\cap	\cup	\cup	\supseteq	⊇
\supset	\supset	\subseteq	\subseteq	\subset	C
\int	ſ	\in		\ o	0
\rfloor	J	\lceil	Γ	\nabla	∇
\lfloor	L	\cdot		\ldots	
\perp	\perp	∖neg	7	\prime	,
∖wedge	\wedge	\times	x	\0	Ø
\rceil	٦	∖surd	\checkmark	\mid	I
\vee	\vee	∖varpi	ω	\copyright	©
\langle	<	∖rangle	\rangle		

You can also specify stream modifiers that control font type and color. The first four modifiers are mutually exclusive. However,

you can use **\fontname** in combination with one of the other modifiers:

- \bf Bold font
- \it Italic font
- \s1 Oblique font (rarely available)
- \rm Normal font
- \fontname{fontname} Specify the name of the font family to use.
- \fontsize{fontsize} Specify the font size in FontUnits.
- \color(colorSpec) Specify color for succeeding characters

Stream modifiers remain in effect until the end of the string or only within the context defined by braces {}.

Specifying Text Color in TeX Strings

Use the \color modifier to change the color of characters following it from the previous color (which is black by default). Syntax is:


• \color{colorname} for the eight basic named colors (red, green, yellow, magenta, blue, black, white), and plus the four Simulink colors (gray, darkGreen, orange, and lightBlue)

Note that short names (one-letter abbreviations) for colors are not supported by the \color modifier.

• \color[rgb]{r g b} to specify an RGB triplet with values between 0 and 1 as a cell array

For example,

```
text(.1,.5,['\fontsize{16}black {\color{magenta}magenta '...
'\color[rgb]{0 .5 .5}teal \color{red}red} black again'])
```



Specifying Subscript and Superscript Characters

The subscript character "_" and the superscript character "^" modify the character or substring defined in braces immediately following.

To print the special characters used to define the TeX strings when Interpreter is Tex, prefix them with the backslash "\" character: \\, \setminus {, \setminus } _, \setminus ^.

See the "Examples" on page 2-3920 in the text reference page for more information.

When Interpreter is set to none, no characters in the String are interpreted, and all are displayed when the text is drawn.

When Interpreter is set to latex, MATLAB provides a complete LaT_EX interpreter for text objects. See the Interpreter property for more information.

Тад

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when you are constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callback routines. You can define Tag as any string.

Туре

string (read only)

Class of graphics object. For text objects, Type is always the string 'text'.

UIContextMenu

handle of a uicontextmenu object

Associate a context menu with the text. Assign this property the handle of a uicontextmenu object created in the same figure as the text. Use the uicontextmenu function to create the context menu. MATLAB displays the context menu whenever you right-click over the text.

Units

```
pixels | normalized | inches |
| characters | centimeters | points | {data}
```

Units of measurement. This property specifies the units MATLAB uses to interpret the Extent and Position properties. All units are measured from the lower left corner of the axes plot box.

- Normalized units map the lower left corner of the rectangle defined by the axes to (0,0) and the upper right corner to (1.0,1.0).
- pixels, inches, centimeters, and points are absolute units (1 point = $\frac{1}{72}$ inch;).

- Units of characters are based on the size of characters in the default system font. The width of one character unit is the width of the letter x, the height of one character unit is the distance between the baselines of two lines of text.
- data refers to the data units of the parent axes as determined by the data graphed (not the axes Units property, which controls the positioning of the axes within the figure window).

If you change the value of Units, it is good practice to return it to its default value after completing your computation so as not to affect other functions that assume Units is set to the default value.

UserData

matrix

User-specified data. Any data you want to associate with the text object. MATLAB does not use this data, but you can access it using set and get.

VerticalAlignment

top | cap | {middle} | baseline |
bottom


Vertical alignment of text. This property specifies the vertical justification of the text string. It determines where MATLAB places the string with regard to the value of the Position property. The possible values mean

- top Place the top of the string's Extent rectangle at the specified *y*-position.
- cap Place the string so that the top of a capital letter is at the specified *y*-position.
- middle Place the middle of the string at the specified *y*-position.
- baseline Place font baseline at the specified y-position.

• bottom — Place the bottom of the string's Extent rectangle at the specified y-position.

The following picture illustrates the alignment options.

Text VerticalAlignment property viewed with the HorizontalAlignment property set to left (the default).



{on} | off

Text visibility. By default, all text is visible. When set to off, the text is not visible, but still exists, and you can query and set its properties.



textread

Purpose	Read data from text file; write to multiple outputs			
	Note textread will be removed in a future version. Use textscan instead.			
Graphical Interface	As an alternative to textread, use the Import Wizard. To activate the Import Wizard, select Import Data from the File menu.			
Syntax	<pre>[A,B,C,] = textread(filename,format) [A,B,C,] = textread(filename,format,N) [] = textread(,param,value,)</pre>			
Description	[A,B,C,] = textread(filename,format) reads data from the file filename into the variables A,B,C, and so on, using the specified format, until the entire file is read. The filename and format inputs are strings, each enclosed in single quotes. textread is useful for reading text files with a known format. textread handles both fixed and free format files.			
	Note When reading large text files, reading from a specific point in a file, or reading file data into a cell array rather than multiple outputs, you might prefer to use the textscan function.			
	textread matches and converts groups of characters from the input. Each input field is defined as a string of non-white-space characters that extends to the next white-space or delimiter character, or to the maximum field width. Repeated delimiter characters are significant, while repeated white-space characters are treated as one.			
	The format string determines the number and types of return arguments. The number of return arguments is the number of items in the format string. The format string supports a subset of the conversion specifiers and conventions of the C language fscanf routine.			

Values for the format string are listed in the table below. White-space characters in the format string are ignored.

format	Action	Output
Literals (ordinary characters)	Ignore the matching characters. For example, in a file that has Dept followed by a number (for department number), to skip the Dept and read only the number, use 'Dept' in the format string.	None
%d	Read a signed integer value.	Double array
%u	Read an integer value.	Double array
%f	Read a floating-point value.	Double array
%S	Read a white-space or delimiter-separated string.	Cell array of strings
%q	Read a double quoted string, ignoring the quotes.	Cell array of strings
%C	Read characters, including white space.	Character array
%[]	Read the longest string containing characters specified in the brackets.	Cell array of strings
%[^]	Read the longest nonempty string containing characters that are not specified in the brackets.	Cell array of strings
%* instead of %	Ignore the matching characters specified by *.	No output
%w instead of %	Read field width specified by w. The %f format supports %w.pf, where w is the field width and p is the precision.	

[A,B,C,...] = textread(filename,format,N) reads the data, reusing the format string N times, where N is an integer greater than zero. If N is smaller than zero, textread reads the entire file.

[...] = textread(...,param,value,...) customizes textread using param/value pairs, as listed in the table below.

textread

param	value	Action
bufsize	Positive integer	Specifies the maximum string length, in bytes. Default is 4095.
commentstyle	matlab	Ignores characters after %.
commentstyle	shell	Ignores characters after #.
commentstyle	с	Ignores characters between /* and */.
commentstyle	C++	Ignores characters after //.
delimiter	One or more characters	Act as delimiters between elements. Default is none.
emptyvalue	Scalar double	Value given to empty cells when reading delimited files. Default is 0.
endofline	Single character or '\r\n'	Character that denotes the end of a line.
		Default is determined from file
expchars	Exponent characters	Default is eEdD.
headerlines	Positive integer	Ignores the specified number of lines at the beginning of the file.
whitespace	Any from the list below:'Space\bBackspace\nNewline\rCarriage return\tHorizontal tab	Treats vector of characters as white space. Default is ' \b\t'.

Note When textread reads a consecutive series of whitespace values, it treats them as one white space. When it reads a consecutive series of delimiter values, it treats each as a separate delimiter.

ı

Remarks If you want to preserve leading and trailing spaces in a string, use the whitespace parameter as shown here:

Examples Example 1 – Read All Fields in Free Format File Using %

The first line of mydata.dat is

Sally Level1 12.34 45 Yes

Read the first line of the file as a free format file using the % format.

```
[names, types, x, y, answer] = textread('mydata.dat', ...
'%s %s %f %d %s', 1)
```

returns

```
names =
    'Sally'
types =
    'Level1'
x =
    12.3400000000000
y =
    45
answer =
    'Yes'
```

Example 2 – Read as Fixed Format File, Ignoring the Floating Point Value

The first line of mydata.dat is

Sally Level1 12.34 45 Yes

Read the first line of the file as a fixed format file, ignoring the floating-point value.

```
[names, types, y, answer] = textread('mydata.dat', ...
'%9c %6s %*f %2d %3s', 1)
returns
names =
Sally
types =
    'Level1'
y =
    45
answer =
    'Yes'
```

f in the format string causes textread to ignore the floating point value, in this case, 12.34.

Example 3 – Read Using Literal to Ignore Matching Characters

The first line of mydata.dat is

Sally Type1 12.34 45 Yes

Read the first line of the file, ignoring the characters Type in the second field.

```
[names, typenum, x, y, answer] = textread('mydata.dat', ...
'%s Type%d %f %d %s', 1)
```

returns

```
names =
    'Sally'
typenum =
    1
x =
    12.3400000000000
y =
    45
```

answer = 'Yes'

Type%d in the format string causes the characters Type in the second field to be ignored, while the rest of the second field is read as a signed integer, in this case, 1.

Example 4 - Specify Value to Fill Empty Cells

For files with empty cells, use the emptyvalue parameter. Suppose the file data.csv contains:

1,2,3,4,,6 7,8,9,,11,12

Read the file using NaN to fill any empty cells:

Example 5 - Read File into a Cell Array of Strings

Read the file fft.m into cell array of strings.

See Also textscan, dlmread, fscanf

textscan

Ρ

Purpose	Read formatted data from text file or string		
Syntax	<pre>C = textscan(fid, 'format') C = textscan(fid, 'format', N) C = textscan(fid, 'format', 'param', value) C = textscan(fid, 'format', N, 'param', value) C = textscan(str,)</pre>		
	[C, position] = textscan()		

Description

Note Before reading a file with textscan, you must open the file with the fopen function. fopen supplies the *fid* input required by textscan. When you are finished reading from the file, close the file by calling fclose(fid).

C = textscan(fid, 'format') reads data from an open text file identified by the file identifier *fid* into cell array *C*. The *format* input is a string of conversion specifiers enclosed in single quotation marks. The number of specifiers determines the number of cells in the cell array C.

C = textscan(fid, 'format', N) reads data from the file, using the format N times, where N is a positive integer. To read additional data from the file after N cycles, call textscan again using the original fid.

C = textscan(fid, 'format', 'param', value) accepts one or more comma-separated parameter name/value pairs. For a list of all valid parameter strings, value descriptions, and defaults, see "User Configurable Options" on page 2-3964.

C = textscan(fid, 'format', N, 'param', value) reads data from the file, using the *format N* times, and using settings specified by pairs of param and value arguments.

 $C = \text{textscan}(str, \ldots)$ reads data from string str. You can use the *format*, N, and parameter/value arguments described above with this syntax. However, for strings, repeated calls to textscan restart the scan from the beginning each time. (To restart a scan from the last position, request a *position* output. See "Example 10 — Resuming a Text Scan of a String" on page 2-3973.)

[C, position] = textscan(...) returns the file or string position at the end of the scan as the second output argument. For a file, this is the value that ftell(fid) would return after calling textscan. For a string, position indicates how many characters textscan read.

Remarks When textscan reads a specified file or string, it attempts to match the data to the *format* string. If textscan fails to convert a data field, it stops reading and returns all fields read before the failure.

Basic Conversion Specifiers

The *format* input is a string of one or more conversion specifiers. The following table lists the basic specifiers.

Field Type	Specifier	Details
Integer, signed	%d	32-bit
	%d8	8-bit
	%d16	16-bit
	%d32	32-bit
	%d64	64-bit
Integer, unsigned	%u	32-bit
	%u8	8-bit
	%u16	16-bit
	%u32	32-bit
	%u64	64-bit
Floating-point	%f	64-bit (double)
number	%f32	32-bit (single)
	%f64	64-bit (double)
	%n	64-bit (double)

Field Type	Specifier	Details	
Character strings	%S %q	String String, where double quotation marks indicate text to keep together	
	%C	Any single character, including a delimiter	
Pattern-matching strings	%[]	Read only characters in the brackets, until the first nonmatching character To include] in the set, specify it first %[]].	
		Example: %[mus] reads 'summer ' as 'summ'.	
	⁹ ∞[^]	Read only characters not in the brackets, until the first matching character. To exclude], specify it first: %[^]].	
		Example: %[^xrg] reads 'summer ' as 'summe'.	

For each numeric conversion specifier, textscan returns a K-by-1 MATLAB numeric vector to the output cell array C, where K is the number of times that textscan finds a field matching the specifier. For each string conversion specifier, textscan returns a K-by-1 cell vector of strings. For each character conversion of the form %Nc (see "Field Length" on page 2-3962), textscan returns a K-by-N character array.

Field Length

You can specify the number of characters or digits to read by inserting a number between the percent character (%) and the format specifier. For floating-point numbers (%n, %f, %f32, %f64), you also can specify the number of digits read to the right of the decimal point.

Specifier	Action Taken		
%NC	Read N characters, including delimiter characters. Example: %9c reads 'Let's Go!' as 'Let's Go!'.		
%Ns %Nn	Read N characters or digits (counting a decimal		
%Nq %Nd	point as a digit), or up to the first delimiter,		
%N[] %Nu	whichever comes first.		
%N[^] %Nf	Example: %5f32 reads '473.238' as 473.2.		
%N.Dn	Read <i>N</i> digits (counting a decimal point as a digit), or up to the first delimiter, whichever comes first. Return <i>D</i> decimal digits in the output.		
%N.Df	Example: %7.2f reads '473.238' as 473.23.		

Skipping Fields or Parts of Fields

The textscan function reads all characters in your file in sequence unless you tell it to ignore a particular field or a portion of a field.

Use the following format specifiers to skip or read portions of fields:

Specifier	Action Taken
%*	Skip the field. textscan does not create an output cell for any field that it skips.
	Example: '%s %*s %s %s %*s %*s %s' (spaces are optional) converts the string 'Blackbird singing in the dead of night' to four output cells with the strings 'Blackbird' 'in' 'the' 'night'
%*n	Ignore <i>n</i> characters of the field, where <i>n</i> is an integer less than or equal to the number of characters in the field. Example: %*4s reads 'summer ' as 'er'.

Specifier	Action Taken
literal	Ignore the specified characters of the field.
	Example: Level%u8 reads 'Level1' as 1.
	Example: %u8Step reads '2Step' as 2.

The textscan function does not include leading white-space characters in the processing of any data fields. When processing numeric data, textscan also ignores trailing white space.

User Configurable Options

This table shows the valid *param-value* options and their default values. Parameter names are not case sensitive.

Parameter	Value	Default
BufSize	Maximum string length in bytes.	4095
CollectOutput	If true, textscan concatenates consecutive output cells with the same data type into a single array.	O (false)
CommentStyle	Symbol(s) designating text to ignore. Specify a single string (such as '%') to ignore characters following the string on the same line. Specify a cell array of two strings (such as { '/* ', '*/ '}) to ignore characters between the strings. textscan checks for comments only at the start	None

Parameter	Value	Default
	of each field, not within a field.	
Delimiter	Field delimiter character(s).	White space
EmptyValue	Value to return for empty numeric fields in delimited files.	NaN
EndOfLine	End-of-line character.	Determined from the file: \n, \r, or \r\n
ExpChars	Exponent characters.	'eEdD'
HeaderLines	Number of lines to skip. (Includes the remainder of the current line.)	0
MultipleDelimsAsOne	If true, textscan treats consecutive delimiters as a single delimiter. Only valid if you specify the Delimiter option.	0 (false)
ReturnOnError	Determines behavior when textscan fails to read or convert. If true, textscan terminates without an error and returns all fields read. If false, textscan terminates with an error and does not return an output cell array.	1 (true)

Parameter	Value	Default
TreatAsEmpty	String(s) in the data file to treat as an empty value. Can be a single string or cell array of strings. Only applies to numeric fields.	None
Whitespace	White-space characters.	'\b\t'

Field and Row Delimiters

Within each row, the default field delimiter is white space. White space can be any combination of space (' '), backspace (' b'), or tab (' t') characters.

If you use the default (white space) field delimiter, textscan interprets repeated white-space characters as a single delimiter. If you specify a nondefault delimiter, textscan interprets repeated delimiter characters as separate delimiters, and returns an empty value to the output cell. (See "Example 5 — Specifying Delimiter and Empty Value Conversion" on page 2-3969 and "Example 7 — Handling Repeated Delimiters" on page 2-3971.)

Rows delimiters are end-of-line (EOL) character sequences. The default end-of-line setting depends on the format of your file, and can include a newline character ('\n'), a carriage return ('\r'), or a combination of the two ('\r\n'). The textscan function uses the end-of-line sequence to determine whether trailing fields on a particular line are empty. Therefore, if the last line of the file contains trailing missing values, but no end-of-line sequence, textscan does not return empty values for those fields.

For more information, see "Example 9 — Using Nondefault Control Characters" on page 2-3972.

Numeric Fields

textscan converts numeric fields to the specified output type according to MATLAB rules regarding overflow, truncation, and the use of NaN, Inf, and -Inf.

For example, MATLAB represents an integer NaN as zero. If textscan finds an empty field associated with an integer format specifier (such as %d or %u), it returns the empty value as zero and not NaN. (See "Example 2 — Reading Different Types of Data" on page 2-3968 and "Example 5 — Specifying Delimiter and Empty Value Conversion" on page 2-3969.)

textscan imports any complex number as a whole into a complex numeric field, converting the real and imaginary parts to the specified numeric type (such as %d or %f). Valid forms for a complex number are as follows:

Form	Example
± <real>±<imag>i j</imag></real>	5.7-3.1i
± <imag>i j</imag>	-7j

Do not include embedded white space in a complex number. textscan interprets embedded white space as a field delimiter.

Examples

Note The following examples include spaces between the conversion specifiers to make the format value easier to read. Spaces are not required.

Example 1 - Reading a String

Read the following string, truncating each value to one decimal digit. The specifier %*1d tells textscan to skip the remaining digit:

str = '0.41 8.24 3.57 6.24 9.27'; C = textscan(str, '%3.1f %*1d'); textscan returns a 1-by-1 cell array C:

 $C{1} = [0.4; 8.2; 3.5; 6.2; 9.2]$

Example 2 – Reading Different Types of Data

Using a text editor, create a file scan1.dat that contains data in the following form:

09/12/2005 Level1 12.34 45 1.23e10 inf Nan Yes 5.1+3i 10/12/2005 Level2 23.54 60 9e19 -inf 0.001 No 2.2-.5i 11/12/2005 Level3 34.90 12 2e5 10 100 No 3.1+.1i

Open the file, and read each column with the appropriate conversion specifier:

```
fid = fopen('scan1.dat');
C = textscan(fid, '%s %s %f32 %d8 %u %f %f %s %f');
fclose(fid);
```

textscan returns a 1-by-9 cell array C with the following cells:

C{1} = {'09/12/2005'; '10/12/2005'; '11/	12/2005'}
	class cell
C{2} = {'Level1'; 'Level2'; 'Level3'}	class cell
$C{3} = [12.34; 23.54; 34.9]$	class single
$C{4} = [45; 60; 12]$	class int8
$C{5} = [4294967295; 4294967295; 200000]$	class uint32
C{6} = [Inf; -Inf; 10]	class double
C{7} = [NaN; 0.001; 100]	class double
C{8} = {'Yes'; 'No'; 'No'}	class cell
C{9} = [5.1+3.0i; 2.2-0.5i; 3.1+0.1i]	class double

The first two elements of C{5} are the maximum values for a 32-bit unsigned integer, or intmax('uint32').

Example 3 – Removing a Literal String

Remove the text 'Level' from each field in the second column of the data from Example 2:

```
fid = fopen('scan1.dat');
C = textscan(fid, '%s Level%u8 %f32 %d8 %u %f %f %s %f');
fclose(fid);
```

textscan returns a 1-by-9 cell array, C, with

C{2} = [1; 2; 3] class uint8

Example 4 – Skipping the Remainder of a Line

Read the first column of the file in Example 2 into a cell array, skipping the rest of the line:

```
fid = fopen('scan1.dat');
dates = textscan(fid, '%s %*[^\n]');
fclose(fid);
```

textscan returns a 1-by-1 cell array dates:

```
dates{1} = {'09/12/2005'; '10/12/2005'; '11/12/2005'}
```

Example 5 – Specifying Delimiter and Empty Value Conversion

Using a text editor, create a comma-delimited file data.csv that contains

Read the file, converting empty cells to - Inf:

```
fid = fopen('data.csv');
C = textscan(fid, '%f %f %f %f %u32 %f', 'delimiter', ',', ...
'EmptyValue', -Inf);
fclose(fid);
```

textscan returns a 1-by-6 cell array C with the following cells:

C{1} = [1; 7] class double

$C{2} = [2;$	8]	class	double				
$C{3} = [3;$	9]	class	double				
$C{4} = [4;$	-Inf]	class	double	(empty	converted	to	-Inf)
$C{5} = [0;$	11]	class	uint32	(empty	converted	to	0)
$C{6} = [6;$	12]	class	double				

textscan converts the empty value in C{4}, associated with a floating-point format, to -Inf. Because MATLAB represents unsigned integer -Inf as 0, textscan converts the empty value in C{5} to 0 and not -Inf.

Example 6 – Using Custom Empty Value Strings and Comments

Using a text editor, create a comma-delimited file data2.csv that contains the lines

abc, 2, NA, 3, 4 // Comment Here def, na, 5, 6, 7

Designate the input that textscan should treat as comments or empty values:

textscan returns a 1-by-5 cell array C with the following cells:

```
C{1} = {'abc'; 'def'}
C{2} = [2; NaN]
C{3} = [NaN; 5]
C{4} = [3; 6]
C{5} = [4; 7]
```

Example 7 – Handling Repeated Delimiters

Using a text editor, create a file data3.csv that contains

```
1,2,3,,4
5,6,7,,8
```

To treat the repeated commas as a single delimiter, use the MultipleDelimsAsOne parameter, with a value of 1:

```
fid = fopen('data3.csv');
C = textscan(fid, '%f %f %f %f %f', 'delimiter', ',', ...
'MultipleDelimsAsOne', 1);
fclose(fid);
```

textscan returns a 1-by-4 cell array C with the following cells:

 $C{1} = [1; 5]$ $C{2} = [2; 6]$ $C{3} = [3; 7]$ $C{4} = [4; 8]$

Example 8 – Using the CollectOutput Switch

Using a text editor, create a file grades.txt that contains

Student_ID	Test1	Test2	Test3
1	91.5	89.2	77.3
2	88.0	67.8	91.0
3	76.3	78.1	92.5
4	96.4	81.2	84.6

The default value for the CollectOutput switch is 0 (false), and textscan returns each column of the numeric data in a separate array:

```
fid = fopen('grades.txt');
% read column headers
C text = textscan(fid, '%s', 4, 'delimiter', '|');
```

```
% read numeric data
C_data0 = textscan(fid, '%d %f %f %f')
C_data0 =
 [4x1 int32] [4x1 double] [4x1 double] [4x1 double]
```

Set CollectOutput to 1 (true) to collect the consecutive columns of the same class (the test scores, which are all double) into a single array:

Example 9 – Using Nondefault Control Characters

When you specify one of the following escape sequences for any parameter value, textscan converts that sequence to the corresponding control character:

- \b Backspace
- \n Newline
- \r Carriage return
- \t Tab
- $\ \ Backslash (\)$

If your data uses a different control character, use the sprintf function to explicitly convert the escape sequence in your call to textscan.

For example, the following string includes a form feed character, \f:

lyric = sprintf('Blackbird\fsinging\fin\fthe\fdead\fof\fnight');

To read the string using textscan, call the sprintf function to explicitly convert the form feed:

```
C = textscan(lyric, '%s', 'delimiter', sprintf('\f'));
```

textscan returns a 1-by-1 cell array C:

```
C{1} =
{'Blackbird'; 'singing'; 'in'; 'the'; 'dead'; 'of'; 'night'}
```

Example 10 – Resuming a Text Scan of a String

If you resume a text scan of a file by calling textscan with the same file identifier (fid), textscan automatically resumes reading at the point where it terminated the last read.

If your input is a string rather than a file, textscan reads from the beginning of the string each time. To resume a scan from any other position in the string, you must use the two-output argument syntax in your initial call to textscan. For example, given the string

lyric = 'Blackbird singing in the dead of night'

Read the first word of the string:

```
[firstword, pos] = textscan(lyric,'%9c', 1);
```

Resume the scan:

```
lastpart = textscan(lyric(pos+1:end), '%s');
```

See Also load | type | importdata | uiimport | dlmread | xlsread | fscanf | fread

- **How To** "Importing Nonrectangular ASCII Data"
 - "Importing Large ASCII Data Sets"

textwrap

Purpose	Wrapped string matrix for given uicontrol
Syntax	outstring = textwrap(h,instring) outstring = textwrap(h,instring,columns) [outstring,position] = textwrap()
Description	outstring = textwrap(h,instring) returns a wrapped string cell array, outstring, that fits inside the uicontrol with handle h. instring is a cell array, with each cell containing a single line of text. outstring is the wrapped string matrix in cell array format. Each cell of the input string is considered a paragraph.
	outstring = textwrap(h,instring,columns) returns an outstring with each line wrapped at columns characters. Spaces are included in the character count.
	[outstring, position] = textwrap() returns the recommended position of the uicontrol in the units of the uicontrol. position considers the extent of the multiline text in the x and y directions.
	textwrap maintains the original line breaks in the input cell array and adds new ones. It can calculate uicontrol positions with any type of Units, including normalized units.
Remarks	When programming a GUI, do not call copyobj or textwrap (which calls copyobj) inside a CreateFcn. The act of copying the uicontrol object fires the CreateFcn repeatedly, which raises a series of error messages after exceeding the root object's RecursionLimit property.
Example	Place two text-wrapped strings in text uicontrols. The left one has a Position calculated by textwrap in Units of pixels; the right one's Position is calculated manually in Units of characters:
	hf = figure('Position',[560 528 350 250]); % Make a text uicontrol to wrap in Units of Pixels % Create it in Units of Pixels, 100 wide, 10 high pos = [10 100 100 10]; ht = uicontrol('Style','Text','Position',pos);

```
string = { 'This is a string for the left text uicontrol.',...
          'to be wrapped in Units of Pixels,',...
          'with a position determined by TEXTWRAP.'};
% Wrap string, also returning a new position for ht
[outstring,newpos] = textwrap(ht,string);
set(ht, 'String', outstring, 'Position', newpos)
% Make another text uicontrol to wrap to a column width of 15
colwidth = 15;
% Create it in Units of Pixels, 100 wide, 10 high
pos1 = [150 \ 100 \ 100 \ 10];
ht1 = uicontrol('Style', 'Text', 'Position', pos1);
string1 = {'This is a string for the right text uicontrol.',...
          'to be wrapped in Units of Characters,',...
          'into lines 15 columns wide.'};
outstring1 = textwrap(ht1,string1,colwidth);
% Reset Units of ht1 to Characters to use the result
set(ht1, 'Units', 'characters')
newpos1 = get(ht1, 'Position');
% Set new Position in Characters to be specified colwidth
% with height the length of the outstring1 cell array + 1.
newpos1(3) = colwidth;
newpos1(4) = length(outstring1)+1;
set(ht1, 'String', outstring1, 'Position', newpos1)
```

📣 Figure 1			
File Edit View Insert 1	Tools Desktop	Window	Help 🕤 🐿
This is a string for the left text uicontrol. to be wrapped in Units of Pixels, with a position determined by TEXTWRAP.	This is a string for the right text uicontrol. to be wrapped in Units of Characters, into lines 15 columns wide.		

See Also align, uicontrol

Purpose	Transpose-free quasi-minimal residual method
Syntax	<pre>x = tfqmr(A,b) x = tfqmr(afun,b) x = tfqmr(a,b,tol) x = tfqmr(a,b,tol,maxit) x = tfqmr(a,b,tol,maxit,m) x = tfqmr(a,b,tol,maxit,m1,m2,x0) [x,flag] = tfqmr(A,B,) [x,flag,relres] = tfqmr(A,b,) [x,flag,relres,y]y(A,b,) [x,flag,relres,iter,resvec] = tfqmr(A,b,)</pre>
Description	 x = tfqmr(A,b) attempts to solve the system of linear equations A*x=b for x. The n-by-n coefficient matrix A must be square and the right-hand side column vector b must have length n. x = tfqmr(afun,b) accepts a function handle afun instead of the matrix A. afun(x) accepts a vector input x and returns the matrix-vector product A*x. In all of the following syntaxes, you can replace A by afun. See "Function Handles" in the MATLAB Programming documentation for more information. "Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide additional parameters to the function afun.
	<pre>x = tfqmr(a,b,tol) specifies the tolerance of the method. If tol is [] then tfqmr uses the default, 1e-6. x = tfqmr(a,b,tol,maxit) specifies the maximum number of iterations. If maxit is [] then tfqmr uses the default, min(N,20). x = tfqmr(a,b,tol,maxit,m) and x = tfqmr(a,b,tol,maxit,m1,m2) use preconditioners m or m=m1*m2 and effectively solve the system A*inv(M)*x = B for x. If M is [] then a preconditioner is not applied. M may be a function handle mfun such that mfun(x) returns m\x. x = tfqmr(a,b,tol,maxit,m1,m2,x0) specifies the initial guess. If x0 is [] then tfqmr uses the default, an all zero vector.</pre>

[x,flag] = tfqmr(A,B,...) also returns a convergence flag:

Flag	Convergence
0	tfqmr converged to the desired tolerance tol within maxit iterations.
1	tfqmr iterated maxit times but did not converge.
2	Preconditioner m was ill-conditioned.
3	tfqmr stagnated. (Two consecutive iterates were the same.)
4	One of the scalar quantities calculated during tfqmr became too small or too large to continue computing.

[x,flag,relres] = tfqmr(A,b,...) also returns the relative residual norm(b-A*x)/norm(b). If flag is 0, then relres <= tol.</pre>

[x,flag,relres,y]y(A,b,...) also returns the iteration number at
which x was computed: 0 <= iter <= maxit.</pre>

[x,flag,relres,iter,resvec] = tfqmr(A,b,...) also returns a vector of the residual norms at each iteration, including norm(b-A*x0).

Examples

```
n = 100; on = ones(n,1);
A = spdiags([-2*on 4*on -on],-1:1,n,n);
b = sum(A,2);
tol = 1e-8;
maxit = 15;
M1 = spdiags([on/(-2) on],-1:0,n,n);
M2 = spdiags([4*on -on],0:1,n,n);
x = tfqmr(A,b,tol,maxit,M1,M2,[]);
```

You can also use a matrix-vector product function as input:

function y = afun(x,n)
y = 4 * x;
y(2:n) = y(2:n) - 2 * x(1:n-1);

y(1:n-1) = y(1:n-1) - x(2:n); x1 = tfqmr(@(x)afun(x,n),b,tol,maxit,M1,M2); If applyOp is a function suitable for use with qmr, it may be used with tfqmr by wrapping it in an anonymous function: x1 = tfqmr(@(x)applyOp(x, 'notransp'),b,tol,maxit,M1,M2); See Also qmr, bicg, bicgstab, bicgstablcgs, gmres, lsqr, luinc, minres, pcg, symmlq, mldivide (\)

throw (MException)

Purpose	Issue exception and terminate function	
Syntax	throw(exception)	
Description	throw(exception) issues an exception based on the information contained in exception. The exception terminates the currently running function and returns control to its caller. The exception argument is scalar object of the MException class that contains information on the cause of the error and where it occurred. The throu- function passes exception back to the caller of the currently running function. and eventually back to the Command Window when the program terminates. The exception is made available to any calling function by means of the catch function, and to the Command Window by means of the MException.last function.	
	Unlike throwAsCaller and rethrow, the throw function also sets the <i>stack</i> field of the <i>exception</i> to the location from which throw was called.	
Remarks	 There are four ways to throw an exception in MATLAB (see the list below). Use the first of these when testing the outcome of some action for failure and reporting the failure to MATLAB. Use one of the remaining three techniques to throw an existing exception. 1 Test the result of some action taken by your program. If the result is found to be incorrect or unexpected, compose an appropriate message and message identifier, and pass these to MATLAB using the error function. 	
	2 Reissue the original exception by throwing the initial exception unmodified. Use the MException rethrow method to do this.	
	3 Collect additional information on the cause of the error, store it in a new or modified exception, and issue a new exception based on that record. Use the MException addCause and throw methods to do this.	

4 Make it appear that the error originated in the caller of the currently running function. Use the MException throwAsCaller method to do this.

Examples Example 1

This example tests the output of function evaluate_plots and throws an exception if it is not acceptable:

```
[minval, maxval] = evaluate_plots(p24, p28, p41);
if minval < lower_bound || maxval > upper_bound
        exception = MException('VerifyOutput:OutOfBounds', ...
        'Results are outside the allowable limits');
        throw(exception);
and
```

end

Example 2

This example attempts to open a file in a folder that is not on the MATLAB path. It uses a nested try-catch block to give the user the opportunity to extend the path. If the file still cannot be found, the program issues an exception with the first error appended to the second using addCause:

```
else
          throw(exception1);
      end
      oldpath = addpath(newFolder);
      trv
         fid = fopen(filename, 'r');
         data = fread(fid);
      catch exception2
         exception3 = addCause(exception2, exception1)
         path(oldpath);
         throw(exception3);
      end
      path(oldpath);
   end
end
fclose(fid);
try
   d = read it('anytextfile.txt');
catch exception
end
exception
exception =
 MException object with properties:
    identifier: 'MATLAB:FileIO:InvalidFid'
       message: 'Invalid file identifier. Use fopen
                 to generate a valid file identifier.'
         stack: [1x1 struct]
         cause: {[1x1 MException]}
  Cannot open file anytextfile.txt. Try another location?y
Enter folder name: xxxxxxx
Warning: Name is nonexistent or not a directory: xxxxxx.
> In path at 110
  In addpath at 89
```

See Also try, catch, error, assert, MException, throwAsCaller(MException), rethrow(MException), addCause(MException), getReport(MException), last(MException)

throwAsCaller (MException)

Purpose	Throw exception as if from calling function
Syntax	throwAsCaller(<i>exception</i>)
Description	throwAsCaller(exception) throws an exception from the currently running function based on the exception input, a scalar object of the MException class. The MATLAB software exits the currently running function and returns control to either the keyboard or an enclosing catch block in a calling function. Unlike the throw function, MATLAB omits the current stack frame from the stack field of the MException, thus making the exception look as if it is being thrown by the caller of the function.
	In some cases, it is not relevant to show the person running your program the true location that generated an exception, but is better to point to the calling function where the problem really lies. You might also find throwAsCaller useful when you want to simplify the error display, or when you have code that you do not want made public.
Remarks	There are four ways to throw an exception in MATLAB (see the list below). Use the first of these when testing the outcome of some action for failure and reporting the failure to MATLAB. Use one of the remaining three techniques to throw an existing exception.
	1 Test the result of some action taken by your program. If the result is found to be incorrect or unexpected, compose an appropriate message and message identifier, and pass these to MATLAB using the error function.
	2 Reissue the original exception by throwing the initial exception unmodified. Use the MException rethrow method to do this.
	3 Collect additional information on the cause of the error, store it in a new or modified exception, and issue a new exception based on that record. Use the MException addCause and throw methods to do this.

4 Make it appear that the error originated in the caller of the currently running function. Use the MException throwAsCaller method to do this.

Examples The function klein_bottle, in this example, generates a Klein Bottle figure by revolving the figure-eight curve defined by XYKLEIN. It defines a few variables and calls the function draw_klein, which executes three functions in a try-catch block. If there is an error, the catch block issues an exception using either throw or throwAsCaller:

```
function klein bottle(pq)
ab = [0 2*pi];
rtr = [2 \ 0.5 \ 1];
box = [-3 \ 3 \ -3 \ 3 \ -2 \ 2];
vue = [55 \ 60];
draw klein(ab, rtr, pq, box, vue)
function draw_klein(ab, rtr, pq, box, vue)
clf
try
   tube('xyklein',ab, rtr, pq, box, vue);
   shading interp
   colormap(pink);
catch exception
   throw(exception)
    throwAsCaller(exception)
%
end
```

Call the klein_bottle function, passing a vector, and the function completes normally by drawing the figure.

klein_bottle([40 40])

Call the function again, this time passing a scalar value. Because the catch block issues the exception using throw, MATLAB displays error messages for line 16 of function draw_klein, and for line 6 of function klein_bottle:

klein_bottle(40)
??? Error using ==> klein_bottle>draw_klein at 16
Attempted to access pq(2); index out of bounds because numel(pq)=1.
Error in ==> klein_bottle at 6
draw_klein(ab, rtr, pq, box, vue)

Run the function again, this time changing the klein_bottle.m file so that the catch block uses throwAsCaller instead of throw. This time, MATLAB only displays the error at line 6 of the main program:

klein_bottle(40)
??? Error using ==> klein_bottle at 6
Attempted to access pq(2); index out of bounds because numel(pq)=1.

See Also try, catch, error, assert, MException, throw(MException), rethrow(MException), addCause(MException), getReport(MException), last(MException)

Purpose	Measure performance using stopwatch timer
Syntax	<pre>tic; any_statements; toc; tic; any_statements; tElapsed=toc; tStart=tic; any_statements; toc(tStart); tStart=tic; any_statements; tElapsed=toc(tStart);</pre>
Description	tic; any_statements; toc; measures the time it takes the MATLAB software to execute the one or more lines of MATLAB code shown here as any_statements. The tic command starts a stopwatch timer, MATLAB executes the block of statements, and toc stops the timer, displaying the time elapsed in seconds.
	tic; any_statements; tElapsed=toc; makes the same time measurement, but assigns the elapsed time output to a variable, tElapsed. MATLAB does not display the elapsed time unless you omit the terminating semicolon. The value returned by toc is a scalar double that represents the elapsed time in seconds.
	tStart=tic; any_statements; toc(tStart); makes the same time measurement, but allows you the option of running more than one stopwatch timer concurrently. You assign the output of tic to a variable tStart and then use that same variable when calling toc. MATLAB measures the time elapsed between the tic and its related toc command and displays the time elapsed in seconds. This syntax enables you to time multiple concurrent operations, including the timing of nested operations.
	tStart=tic; any_statements; tElapsed=toc(tStart); is the same as the command shown above, except that MATLAB assigns the elapsed time output to a variable, tElapsed. MATLAB does not display the elapsed time unless you omit the terminating semicolon. The value returned by toc is a scalar double that represents the elapsed time in seconds.
Remarks	Using the third syntax shown above, you can nest tic-toc pairs.

	When using the simpler tic and toc syntax, avoid using consecutive tics as they merely overwrite the internally-recorded starting time. Consecutive tocs however, may be useful as each toc returns the increasing time that has elapsed since the most recent tic. Using this mechanism, you can take multiple measurements from a single point in time.
	When using the tStart=tic and toc(tStart) syntax, it is advisable to select a unique variable for tStart. If you accidentally overwrite this variable prior to the toc for which it is needed, you will get inaccurate results for the time measurement.
	tStart is a 64-bit unsigned integer, scalar value. This value is only useful as an input argument for a subsequent call to toc.
	The clear function does not reset the starting time recorded by a tic command.
Examples	Measure how the time required to solve a linear system varies with the order of a matrix:
	<pre>for n = 1:100 A = rand(n,n); b = rand(n,1); tic x = A\b; t(n) = toc; end plot(t)</pre>
	Measure the minimum and average time to compute a summation of Bessel functions:
	<pre>BEPS = 1000: minTime = Inf: nsum = 10:</pre>

```
REPS = 1000; minTime = Inf; nsum = 10;
tic;
for i=1:REPS
  tStart = tic; total = 0;
  for j=1:nsum,
```

```
total = total + besselj(j,REPS);
end
tElapsed = toc(tStart);
minTime = min(tElapsed, minTime);
end
averageTime = toc/REPS;
```

See Also clock, cputime, etime, profile

Purpose	MATLAB Gateway to LibTIFF library routines
Description	The Tiff class represents a connection to a Tagged Image File Format (TIFF) file and provides access to many of the capabilities of the LibTIFF library. Use the methods of the Tiff object to call routines in the LibTIFF library. While you can use the imread and imwrite functions to read and write TIFF files, the Tiff class offers capabilities that these functions don't provide, such as reading subimages, writing tiles and strips of image data, and modifying individual TIFF tags.
	In most cases, the syntax of the Tiff method is similar to the syntax of the corresponding LibTIFF library function. To get the most out of the Tiff object, you must be familiar with the LibTIFF version 3.7.1 API, as well as the TIFF specification and technical notes. View this documentation at LibTIFF - TIFF Library and Utilities
	For copyright information, see the libtiffcopyright.txt file.
Construction	<pre>obj = Tiff(filename,mode) creates a Tiff object associated with the TIFF file filename. mode specifies the type of access to the file.</pre>
	A TIFF file is made up of one or more image file directories (IFDs). An IFD contains image data and associated metadata. IFDs can also contain subIFDs which also contain image data and metadata. When you open a TIFF file for reading, the Tiff object makes the first IFD in the file the <i>current</i> IFD. Tiff methods operate on the current IFD. You can use Tiff object methods to navigate among the IFDs and the subIFDs in a TIFF file.
	When you open a TIFF file for writing or appending, the Tiff object automatically creates a IFD in the file for writing subsequent data. This IFD has all the default values specified in TIFF Revision 6.0.
	When creating a new TIFF file, before writing any image to the file, you must create certain required fields (tags) in the file. These tags include ImageWidth, ImageHeight, BitsPerSample, SamplesPerPixel, Compression, PlanarConfiguration, and Photometric. If the image data has a stripped layout, the IFD contains the RowsPerStrip tag. If

the image data has a tiled layout, the IFD contains the TileWidth and TileHeight tags. Use the setTag method to define values for these tags.

Inputs

filename

Text string specifying name of file.

mode

One of the following text strings specifying the type of access to the TIFF file.

Supported Values

Parameter	Description	
'r'	Open file for reading	
'w'	Open file for writing; discard existing contents	
'a'	Open or create file for writing; append data to end of file.	
'r+'	Open (do not create) file for reading and writing	

Properties Compression

Specify scheme used to compress image data

This property identifies all supported values for the Compression tag. You can use this property to specify the value of this tag when using the setTag method.

Supported Values

None

CCITTRLE (Read-only)

CCITTFax3

CCITTFax4
LZW
JPEG
CCITTRLEW (Read-only)
PackBits
SGILog
SGILog24
Deflate
AdobeDeflate (Same as deflate

Example:

tiffobj.setTag('Compression', Tiff.Compression.JPEG);

ExtraSamples

Describe extra components

This property identifies all supported values for the ExtraSamples tag. Use this property to specify the value of this tag when using the setTag method.

Supported Values

Unspecified	
AssociatedAlpha	
UnassociatedAlpha	

Example:

```
tiffobj.setTag('ExtraSamples', Tiff.ExtraSamples.AssociatedAlpha)
```

InkSet

Specify set of inks used in separated image

This property identifies all supported values for the InkSet tag. Use this property to specify the value of this tag when using the setTag method. In this context, separated refers to photometric interpretation, not the planar configuration.

Supported Values

СМҮК	Order of components: cyan, magenta, yellow, black. Usually, a value of 0 represents 0% ink coverage and a value of 255 represents 100% ink coverage for that component, but consult the TIFF specification for DotRange. When you specify CMYK, do not set the InkNames tag.
MultiInk	Any ordering other than CMYK. Consult the TIFF specification for InkNames field for a description of the inks used.

Example:

```
tiffobj.setTag('InkSet', Tiff.InkSet.CMYK);
```

Orientation

Specify visual orientation of the image data.

This property identifies all supported values for the Orientation tag. The first row represents the top of the image, and the first column represents the left side. Use this property to specify the value of this tag when using the setTag method. Support for this tag is for informational purposes only, and it does not affect how MATLAB reads or writes the image data.

Supported Values

TopLeft

TopRight

BottomRight

BottomLeft
LeftTop
RightTop
RightBottom
LeftBottom

Example:

```
tiffobj.setTag('Orientation', Tiff.Orientation.TopRight);
```

Photometric

Specify color space of image data

This property identifies all supported values for the Photometric tag. Use this property to specify the value of this tag when using the setTag method.

Supported Values

MinIsWhite
MinIsBlack
RGB
Palette
Mask
Separated (CMYK)
YCbCr
CIELab
ICCLab
ITULab
LogL
LogLUV

CFA

LinearRaw

Example:

```
tiffobj.setTag('Photometric', Tiff.Photometric.RGB);
```

PlanarConfiguration

Specifies how image data components are stored on disk

This property identifies all supported values for the PlanarConfiguration tag. Use this property to specify the value of this tag when using the setTag method.

Supported Values

Chunky	Store component values for each pixel contiguously. For example, in the case of RGB data, the first three pixels would be stored in the file as RGBRGBRGB etc. Almost all TIFF images have contiguous planar configurations.
Separate	Store component values for each pixel separately. For example, in the case of RGB data, the red component would be stored separately in the file from the green and blue components.

Example:

tiffobj.setTag('PlanarConfiguration', Tiff.PlanarConfiguration

ResolutionUnit

Specify unit of measurement used for $\ensuremath{\mathsf{XResolution}}$ and $\ensuremath{\mathsf{YResolution}}$ tags

This property identifies all supported values for the XResolution and YResolution tags. Use this property to specify the value of this tag when using the setTag method.

Supported Values

None (default)	
Inch	
Centimeter	

Example:

```
tiffobj.setTag('YResolution', Tiff.ResolutionUnit.Inch);
```

SampleFormat

Specify how to interpret each pixel sample

This property identifies all supported values for the SampleFormat tag. Use this property to specify the value of this tag when using the setTag method.

Supported Values

Uint
Int
IEEEFP
Void
ComplexInt
ComplexIEEEFP

Example:

```
tiffobj.setTag('SampleFormat', Tiff.SampleFormat.IEEEFP);
```

SGILogDataFmt

Specify control of client data for SGILog codec

These enumerated values should only be used when the photometric interpretation value is LogL or LogLUV. The BitsPerSample, SamplesPerPixel, and SampleFormat tags should not be set if the image type is LogL or LogLuv. The choice of SGILogDataFmt will set these tags automatically. The Float and Bits8 settings imply a SamplesPerPixel value of 3 for LogLUV images, but only 1 for LogL images.

Supported Values

Float	Single precision samples
Bits8	uint8 samples (read only)

This tag can be set only once per instance of a LogL/LogLuv Tiff image object instance.

Example:

```
tiffobj = Tiff('example.tif','r');
tiffobj.setDirectory(3); % image three is a LogLuv image
tiffobj.setTag('SGILogDataFmt', Tiff.SGILogDataFmt.Float);
imdata = tiffobj.read();
```

SubFileType

Specify type of image

This property identifies all supported values for the SubFileType tag. SubFileType is a bitmask that indicates the type of the image. Use this property to specify the value of this tag when using the setTag method.

Supported Values

Default	Default value for single image file or first image.
ReducedImage	The current image is a thumbnail or reduced-resolution image that typically would be found in a sub-IFD.
Page	The image is a single image of a multi-image (or multipage) file.
Mask	The image is a transparency mask for another image in the file. The photometric interpretation value must be Photometric.Mask.

Example:

tiffobj.setTag('SubFileType', Tiff.SubFileType.Mask);

TagID

List of recognized TIFF tag names with their ID numbers

This property identifies all the supported TIFF tags with their ID numbers. Use this property to specify a tag when using the setTag method. For example, Tiff.TagID.ImageWidth returns the ID of the ImageWidth tag. To get a list of the names of supported tags, use the getTagNames method.

Example:

tiffobj.setTag(Tiff.TagID.ImageWidth, 300);

Thresholding

Specifies technique used to convert from gray to black and white pixels.

This property identifies all supported values for the Thresholding tag. Use this property to specify the value of this tag when using the setTag method.

Supported Values

BiLevel (default)

HalfTone

ErrorDiffuse

Example:

tiffobj.setTag('Thresholding', Tiff.Thresholding.HalfTone);

YCbCrPositioning

Specify relative positioning of chrominance samples

This property identifies all supported values for the YCbCrPositioning tag. This property specifies the positioning of chrominance components relative to luminance samples. Use this property to specify the value of this tag when using the setTag method.

Supported Values

Centered	Specify for compatibility with industry standards such as PostScript Level 2
Cosited	Specify for compatibility with most digital video standards such as CCIR Recommendation 601-1.

Example:

```
tiffobj.setTag('YCbCrPositioning', Tiff.YCbCrPositioning.Cente
```

Methods

close

Close Tiff object

computeStrip

Index number of strip containing specified coordinate

computeTile	Index number of tile containing specified coordinates
currentDirectory	Index of current IFD
getTag	Value of specified tag
getTagNames	List of recognized TIFF tags
getVersion	LibTIFF library version
isTiled	Determine if tiled image
lastDirectory	Determine if current IFD is last in file
nextDirectory	Make next IFD current IFD
numberOfStrips	Total number of strips in image
numberOfTiles	Total number of tiles in image
read	Read entire image
readEncodedStrip	Read data from specified strip
readEncodedTile	Read data from specified tile
rewriteDirectory	Write modified metadata to existing IFD
setDirectory	Make specified IFD current IFD
setSubDirectory	Make subIFD specified by byte offset current IFD
setTag	Set value of tag
write	Write entire image
writeDirectory	Create new IFD and make it current IFD
writeEncodedStrip	Write data to specified strip
writeEncodedTile	Write data to specified tile

Examples	Create a new TIFF file using the Tiff object. To run this example, your directory must be writable.
	t = Tiff('myfile.tif', 'w'); %
	% Close the Tiff object t.close();
See Also	imread imwrite
Tutorials	 "Exporting Image Data and Metadata to TIFF Files" "Reading Image Data and Metadata from TIFF Files"

Purpose	Construct timer object
Syntax	<pre>T = timer T = timer('PropertyName1', PropertyValue1, 'PropertyName2',</pre>
Description	T = timer constructs a timer object with default attributes.
	T = timer('PropertyName1', PropertyValue1, 'PropertyName2', PropertyValue2,) constructs a timer object in which the given property name/value pairs are set on the object. See "Timer Object Properties" on page 2-4002 for a list of all the properties supported by the timer object.
	Note that the property name/property value pairs can be in any format supported by the set function, i.e., property/value string pairs, structures, and property/value cell array pairs.
Examples	This example constructs a timer object with a timer callback function handle, mycallback, and a 10 second interval.
	t = timer('TimerFcn',@mycallback, 'Period', 10.0);
Timer Object Properties	The timer object supports the following properties that control its attributes. The table includes information about the data type of each property and its default value.
-	To view the value of the properties of a particular timer object, use the get(timer) function. To set the value of the properties of a timer object, use the set(timer) function.

Property Name	Property Description	Data Typ Access	es, Values, Defaults,
AveragePeriod	Average time between TimerFcn executions since	Data type	double
	the timer started.	Default	NaN
	Note: Value is NaN until timer executes two timer callbacks.	Read only	Always
BusyMode	Action taken when a timer has to execute TimerFcn	Data type	Enumerated string
of p Time 'c the 'e erro be s	before the completion of previous execution of TimerFcn.	Values	'drop' 'error' 'queue'
	'drop' — Do not execute	Default	'drop'
	the function. 'error' — Generate an error. Requires ErrorFcn to be set. 'gueue' — Execute	Read only	While Running = 'on'
	function at next opportunity.		
ErrorFcn	Function that the timer executes when an error	Data type	Text string, function handle, or cell array
	occurs. This function executes before the StopFcn.	Default	None
	See "Creating Callback Functions" for more information.	Read only	Never

Property Name	Property Description	Data Types, Values, Defaults, Access	
ExecutionMode	Determines how the timer object schedules timer events. See "Timer Object Execution Modes" for more information.	Data type	Enumerated string
		Values	'singleShot' 'fixedDelay' 'fixedRate' 'fixedSpacing'
		Default	'singleShot'
		Read only	While Running = 'on'
InstantPeriod	The time between the last two executions of TimerFcn.	Data type	double
		Default	NaN
		Read only	Always
Name	User-supplied name.	Data type	Text string
		Default	'timer- <i>i</i> ', where <i>i</i> is a number indicating the <i>i</i> th timer object created this session. To reset <i>i</i> to 1, execute the clear classes command.
		Read only	Never

Property Name	Property Description	Data Typ Access	es, Values, Defaults,
ObjectVisibility	Provides a way for application developers	Data type	Enumerated string
	to prevent end-user access to the timer objects created by their application. The	Values	'off' 'on'
	timerfind function does	Default	'on'
	not return an object whose ObjectVisibility property is set to 'off'. Objects that are not visible are still valid. If you have access to the object (for example, from within the file that created it), you can set its properties.	Read only	Never
Period	Specifies the delay, in seconds, between executions of TimerFcn.	Data type	double
		Value	Any number >= 0.001
		Default	1.0
		Read only	While Running = 'on'
Running	Indicates whether the timer is currently executing.	Data type	Enumerated string
		Values	'off' 'on'
		Default	'off'
		Read only	Always

Property Name	Property Description	Data Typ Access	es, Values, Defaults,
StartDelay	Specifies the delay, in seconds, between the start	Data type	double
	of the timer and the first execution of the function	Values	Any number >= 0
	specified in TimerFcn.	Default	0
		Read only	While Running = 'on'
StartFcn	Function the timer calls when it starts. See "Creating	Data type	Text string, function handle, or cell array
	Callback Functions" for more information.	Default	None
		Read only	Never
StopFcn	Function the timer calls when it stops. The timer stops when	Date type	Text string, function handle, or cell array
		Default	None
	• You call the timer stop function	Read only	Never
	 The timer finishes executing TimerFcn, i.e., the value of TasksExecuted reaches the limit set by TasksToExecute. An error occurs (The ErrorFcn is called first, followed by the StopFcn.) 		

Property Name	Property Description	Data Types, Values, Defaults, Access	
	See "Creating Callback Functions" for more information.		
Tag	User supplied label.	Data type	Text string
		Default	Empty string (' ')
		Read only	Never
TasksToExecute	Specifies the number of times the timer should execute the function specified in the TimerFcn property.	Data type	double
		Values	Any number > 0
		Default	Inf
		Read only	Never
TasksExecuted	The number of times the timer has called TimerFcn since the timer was started.	Data type	double
		Values	Any number ≥ 0
		Default	0
		Read only	Always
TimerFcn	Timer callback function. See "Creating Callback Functions" for more information.	Data type	Text string, function handle, or cell array
		Default	None
		Read only	Never

Property Name	Property Description	Data Types, Values, Defaults, Access	
Туре	Identifies the object type.	Data type	Text string
		Values	'timer'
		Read only	Always
UserData	User-supplied data.	Data type	User-defined
		Default	[]
		Read only	Never

See Also delete(timer), disp(timer), get(timer), isvalid(timer), set(timer), start, startat, stop, timerfind, timerfindall, wait

timerfind

Purpose	Find timer objects
Syntax	<pre>out = timerfind out = timerfind('P1', V1, 'P2', V2,) out = timerfind(S) out = timerfind(obj, 'P1', V1, 'P2', V2,)</pre>
Description	out = timerfind returns an array, out, of all the timer objects that exist in memory.
	out = timerfind('P1', V1, 'P2', V2,) returns an array, out, of timer objects whose property values match those passed as parameter/value pairs, P1, V1, P2, V2. Parameter/value pairs may be specified as a cell array.
	<pre>out = timerfind(S) returns an array, out, of timer objects whose property values match those defined in the structure, S. The field names of S are timer object property names and the field values are the corresponding property values.</pre>
	out = timerfind(obj, 'P1', V1, 'P2', V2,) restricts the search for matching parameter/value pairs to the timer objects listed in obj. Obj can be an array of timer objects.
	Note When specifying parameter/value pairs, you can use any mixture of strings, structures, and cell arrays in the same call to timerfind.

Note that, for most properties, timerfind performs case-sensitive searches of property values. For example, if the value of an object's Name property is 'MyObject', timerfind will not find a match if you specify 'myobject'. Use the get function to determine the exact format of a property value. However, properties that have an enumerated list of possible values are not case sensitive. For example, timerfind will find an object with an ExecutionMode property value of 'singleShot' or 'singleshot'.

timerfind

Examples These examples use timerfind to find timer objects with the specified
property values.
 t1 = timer('Tag', 'broadcastProgress', 'Period', 5);
 t2 = timer('Tag', 'displayProgress');
 out1 = timerfind('Tag', 'displayProgress')
 out2 = timerfind({'Period', 'Tag'}, {5, 'broadcastProgress'})
See Also get(timer), timer, timerfindall

Purpose	Find timer objects, including invisible objects
Syntax	<pre>out = timerfindall out = timerfindall('P1', V1, 'P2', V2,) out = timerfindall(S) out = timerfindall(obj, 'P1', V1, 'P2', V2,)</pre>
Description	<pre>out = timerfindall returns an array, out, containing all the timer objects that exist in memory, regardless of the value of the object's ObjectVisibility property.</pre>
	out = timerfindall('P1', V1, 'P2', V2,) returns an array, out, of timer objects whose property values match those passed as parameter/value pairs, P1, V1, P2, V2. Parameter/value pairs may be specified as a cell array.
	<pre>out = timerfindall(S) returns an array, out, of timer objects whose property values match those defined in the structure, S. The field names of S are timer object property names and the field values are the corresponding property values.</pre>
	out = timerfindall(obj, 'P1', V1, 'P2', V2,) restricts the search for matching parameter/value pairs to the timer objects listed in obj. obj can be an array of timer objects.
	Note When specifying parameter/value pairs, you can use any mixture of strings, structures, and cell arrays in the same call to timerfindall.
	Note that for most monotice, time of indell monformer and itime

Note that, for most properties, timerfindall performs case-sensitive searches of property values. For example, if the value of an object's Name property is 'MyObject', timerfindall will not find a match if you specify 'myObject'. Use the get function to determine the exact format of a property value. However, properties that have an enumerated list of possible values are not case sensitive. For example, timerfindall will find an object with an ExecutionMode property value of 'singleShot' or 'singleshot'.

timerfindall

Examples Create several timer objects.

t1 = timer; t2 = timer; t3 = timer;

Set the ObjectVisibility property of one of the objects to 'off'.

```
t2.ObjectVisibility = 'off';
```

Use timerfind to get a listing of all the timer objects in memory. Note that the listing does not include the timer object (timer-2) whose ObjectVisibility property is set to 'off'.

timerfind

Timer Object Array

Index:	ExecutionMode:	Period:	TimerFcn:	Name:
1	singleShot	1	1.1	timer-1
2	singleShot	1	1.1	timer-3

Use timerfindall to get a listing of all the timer objects in memory. This listing includes the timer object whose ObjectVisibility property is set to 'off'.

timerfindall

Timer Object Array

Index:	ExecutionMode:	Period:	TimerFcn:	Name:
1	singleShot	1	1.1	timer-1
2	singleShot	1	1.1	timer-2
3	singleShot	1	1.1	timer-3

See Also

get(timer), timer, timerfind

Purpose	Create timeseries object
Syntax	<pre>ts = timeseries ts = timeseries(Data) ts = timeseries(Name) ts = timeseries(Data,Time) ts = timeseries(Data,Time,Quality) ts = timeseries(Data,,'Parameter',Value,)</pre>
Description	<pre>ts = timeseries creates an empty time-series object. ts = timeseries(Data) creates a time series with the specified Data, which can be an array of samples. ts has a default time vector that ranges from 0 to N-1 with a 1-second interval, where N is the number of samples. The default name of the timeseries object is 'unnamed'.</pre>
	<pre>ts = timeseries(Name) creates an empty time series with the name specified by a string Name. This name can differ from the time-series variable name.</pre>
	ts = timeseries(Data,Time) creates a time series with the specified Data array and time vector Time. The time vector can contain duplicate values but not decreasing values. When time values are date strings, you must specify Time as a cell array of date strings.
	<pre>ts = timeseries(Data,Time,Quality) creates a timeseries object. The Quality attribute is an integer vector with values-128 to 127 that specifies the quality in terms of codes defined by QualityInfo.Code.</pre>
	ts = timeseries(Data,,'Parameter',Value,) creates a timeseries object with optional parameter-value pairs after the Data, Time, and Quality arguments. You can specify the following parameters:
	• Name — Time-series name entered as a string
	• IsTimeFirst — Logical value (true or false) specifying whether the time vector runs along the first or last dimension of the data array. You can set this property when a 2-D data array is square

and, therefore, the dimension that is aligned with time is ambiguous. 3-D and higher-dimension data requires IsTimeFirst to be false; for such data, time steps always lie along the last dimension. The property value defaults to true.

Note In a future release, IsTimeFirst will default to false for 3-D and an higher-dimensional data, and setting IsTimeFirst to true for such data will generate an error.

Remarks Definition: timeseries

The time-series object, called timeseries, is a MATLAB variable that contains time-indexed data and properties in a single, coherent structure. For example, in addition to data and time values, you can also use the time-series object to store events, descriptive information about data and time, data quality, and the interpolation method.

Definition: Data Sample

A time-series *data sample* consists of one or more values recorded at a specific time. The number of data samples in a time series is the same as the length of the time vector.

For example, suppose that ts.data has the size 3-by-4-by-5 and the time vector has the length 5. Then, the number of samples is 5 and the total number of data values is $3 \times 4 \times 5 = 60$.

Duplicate Time Values

A timeseries object can include duplicate time values. The time vector must obey two conditions:

- Duplicated values must occupy contiguous elements.
- Time values must be non-decreasing.

Interpolating time series data using methods like resample and synchronize can produce different results when the input timeseries contains duplicate times than when time values are not duplicated.

Notes About Quality

When Quality is a vector, it must have the same length as the time vector. In this case, each Quality value applies to the corresponding data sample. When Quality is an array, it must have the same size as the data array. In this case, each Quality value applies to the corresponding data value of the ts.data array.

Examples Example 1 – Using Default Time Vector

Create a timeseries object called 'LaunchData' that contains four data sets, each stored as a column of length 5 and using the default time vector:

```
b = timeseries(rand(5, 4), 'Name', 'LaunchData')
```

Example 2 – Using Uniform Time Vector

Create a timeseries object containing a single data set of length 5 and a time vector starting at 1 and ending at 5:

```
b = timeseries(rand(5,1), [1 2 3 4 5])
```

Example 3

Create a timeseries object called 'FinancialData' containing five data points at a single time point:

b = timeseries(rand(1,5),1,'Name','FinancialData')

See Also addsample, tscollection, tsdata.event, tsprops

title

Purpose	Add title to current axes
GUI Alternative	To create or modify a plot's title from a GUI, use Insert Title from the figure menu. Use the Property Editor, one of the plotting tools , to modify the position, font, and other properties of a legend. For details, see The Property Editor in the MATLAB Graphics documentation.
Syntax	<pre>title('string') title(fname) title(,'PropertyName',PropertyValue,) title(axes_handle,) h = title()</pre>
Description	<pre>Each axes graphics object can have one title. The title is located at the top and in the center of the axes. title('string') outputs the string at the top and in the center of the current axes. title(fname) evaluates the function that returns a string and displays the string at the top and in the center of the current axes. title(,'PropertyName', PropertyValue,) specifies property name and property value pairs for the text graphics object that title creates. Do not use the 'String' text property to set the title string; the content of the title should be given by the first argument. title(axes_handle,) adds the title to the specified axes. h = title() returns the handle to the text object used as the title.</pre>

Note The words default, factory, and remove are reserved words that will not appear in a title when quoted as a normal string. In order to display any of these words individually, type '\reserved_word' instead of 'reserved_word'.

Examples Display today's date in the current axes:

```
title(date)
```

Include a variable's value in a title:

```
f = 70;
c = (f-32)/1.8;
title(['Temperature is ',num2str(c),'C'])
```

Make a multi-colored title:

```
title(['\fontsize{16}black {\color{magenta}magenta '...
'\color[rgb]{0 .5 .5}teal \color{red}red} black again'])
```

Include a variable's value in a title and set the color of the title to yellow:

```
n = 3;
title(['Case number #',int2str(n)],'Color','y')
```

Include Greek symbols in a title:

```
title('\ite^{\omega\tau} = cos(\omega\tau) + isin(\omega\tau)')
```

Include a superscript character in a title:

title('\alpha^2')

Include a subscript character in a title:

```
title('X_1')
```

The text object String property lists the available symbols.

Create a multiline title using a multiline cell array.

```
title({'First line';'Second line'})
```

Remarks	title sets the Title property of the current axes graphics object to a new text graphics object. See the text String property for more information.
See Also	gtext, int2str, num2str, text, xlabel, ylabel, zlabel "Annotating Plots" on page 1-97 for related functions
	Text Properties for information on setting parameter/value pairs in titles
	Adding Titles to Graphs for more information on ways to add titles

Purpose	Convert CDF epoch object to MATLAB datenum
Syntax	n = todatenum(obj)
Description	n = todatenum(obj) converts the CDF epoch object ep_obj into a MATLAB serial date number. Note that a CDF epoch is the number of milliseconds since 01-Jan-0000 whereas a MATLAB datenum is the number of days since 00-Jan-0000.
Examples	Construct a CDF epoch object from a date string, and then convert the object back into a MATLAB date string:
	dstr = datestr(today) dstr = 08-0ct-2003
	<pre>obj = cdfepoch(dstr) obj = cdfepoch object: 08-0ct-2003 00:00:00</pre>
	dstr2 = datestr(todatenum(obj)) dstr2 = 08-0ct-2003
See Also	cdfepoch, cdfinfo, cdfread, cdfwrite, datenum

toeplitz

Purpose	Toeplitz matrix		
Syntax	T = toeplitz(c,r) T = toeplitz(r)		
Description	A <i>Toeplitz</i> matrix is defined by one row and one column. A <i>symmetric Toeplitz</i> matrix is defined by just one row. toeplitz generates Toeplitz matrices given just the row or row and column description.		
	T = toeplitz(c,r) returns a nonsymmetric Toeplitz matrix T having c as its first column and r as its first row. If the first elements of c and r are different, a message is printed and the column element is used.		
	For a real vector $r, T = toeplitz(r)$ returns the symmetric Toeplitz matrix formed from vector r , where r defines the first row of the matrix. For a complex vector r with a real first element, $T = toeplitz(r)$ returns the Hermitian Toeplitz matrix formed from r , where r defines the first row of the matrix and r' defines the first column. When the first element of r is not real, the resulting matrix is Hermitian off the		
	main diagonal, i.e., $T_{ij} = conj(T_{ji})$ for $i \neq j$.		
Examples	A Toeplitz matrix with diagonal disagreement is $c = [1 \ 2 \ 3 \ 4 \ 5];$ $r = [1.5 \ 2.5 \ 3.5 \ 4.5 \ 5.5];$ toeplitz(c,r) Column wins diagonal conflict: ans = $1.000 \ 2.500 \ 3.500 \ 4.500 \ 5.500$ $2.000 \ 1.000 \ 2.500 \ 3.500 \ 4.500$ $3.000 \ 2.000 \ 1.000 \ 2.500 \ 3.500$ $4.000 \ 3.000 \ 2.000 \ 1.000 \ 2.500$		
See Also	hankel, kron		

Purpose	Root folder for specified toolbox
Syntax	<pre>toolboxdir('tbxFolderName') s = toolboxdir('tbxFolderName') s = toolboxdir tbxFolderName</pre>
Description	toolboxdir('tbxFolderName') returns a string that is the absolute path to the specified toolbox, tbxFolderName, where tbxFolderName is the folder name for the toolbox.
	s = toolboxdir('tbxFolderName') returns the absolute path to the specified toolbox to the output argument, $s.$
	s = toolboxdir tbxFolderName is the command form of the syntax.
Remarks	toolboxdir is particularly useful for MATLAB Compiler software. The base folder of all toolboxes installed with MATLAB software is:
	<pre>matlabroot/toolbox/tbxFolderName</pre>
	However, in deployed mode, the base folders of the toolboxes are different. toolboxdir returns the correct root folder, whether running from MATLAB or from an application deployed with the MATLAB Compiler software.
Example	Obtain the path for the Control System Toolbox software:
	<pre>s = toolboxdir('control')</pre>
	MATLAB returns:
	<pre>s = \\myhome\r2009a\matlab\toolbox\control</pre>
See Also	ctfroot (in the MATLAB Compiler product), fullfile, matlabroot, path,
	"Managing Files in MATLAB"

trace

Purpose	Sum of diagonal elements
Syntax	b = trace(A)
Description	b = trace(A) is the sum of the diagonal elements of the matrix A.
Algorithm	trace is a single-statement M-file.
	<pre>t = sum(diag(A));</pre>
See Also	det, eig

Purpose	Transpose timeseries object
Syntax	ts1 = transpose(ts)
Description	<pre>ts1 = transpose(ts) returns a new timeseries object ts1 with IsTimeFirst value set to the opposite of what it is for ts. For example, if ts has the first data dimension aligned with the time vector, ts1 has the last data dimension aligned with the time vector.</pre>
Remarks	The transpose function that is overloaded for the timeseries objects does not transpose the data. Instead, this function changes whether the first or the last dimension of the data is aligned with the time vector.
	Note To transpose the data, you must transpose the Data property of the time series. For example, you can use the syntax transpose(ts.Data) or (ts.Data).'. Data must be a 2-D array.
	Consider a time series with 10 samples with the property IsTimeFirst = True. When you transpose this time series, the data size is changed from 10-by-1 to 1-by-1-by-10. Note that the first dimension of the Data property is shown explicitly.
	The following table summarizes how the size for time-series data (up to three dimensions) display before and after transposing.
	Data Size Before and After Transposing

Size of Original Data	Size of Transposed Data
N-by-1	1-by-1-by-N
N-by-M	M-by-1-by-N
N-by-M-by-L	M-by-L-by-N

Examples Suppose that a timeseries object ts has ts.Data size 10-by-3-by-2 and its time vector has a length of 10. The IsTimeFirst property of ts is set to true, which means that the first dimension of the data is aligned with the time vector. transpose(ts) modifies the timeseries object such that the last dimension of the data is now aligned with the time vector. This permutes the data such that the size of ts.Data becomes 3-by-2-by-10.

See Also ctranspose (timeseries), tsprops

Purpose	Trapezoidal numerical integration
Syntax	Z = trapz(Y) Z = trapz(X,Y) Z = trapz(,dim)
Description	Z = trapz(Y) computes an approximation of the integral of Y via the trapezoidal method (with unit spacing). To compute the integral for spacing other than one, multiply Z by the spacing increment. Input Y can be complex.
	If Y is a vector, trapz(Y) is the integral of Y .
	If Y is a matrix, trapz(Y) is a row vector with the integral over each column.
	If Y is a multidimensional array, trapz(Y) works across the first nonsingleton dimension.
	Z = trapz(X,Y) computes the integral of Y with respect to X using trapezoidal integration. Inputs X and Y can be complex.
	If X is a column vector and Y an array whose first nonsingleton dimension is $length(X)$, $trapz(X,Y)$ operates across this dimension.
	Z = trapz(,dim) integrates across the dimension of Y specified by scalar dim. The length of X, if given, must be the same as $size(Y,dim)$.
Examples	Example 1
	The exact value of $\int_0^{\pi} \sin(x) dx$ is 2. To approximate this numerically on a uniformly spaced grid, use
	X = 0:pi/100:pi; Y = sin(X);
	Then both
	Z = trapz(X, Y)

and

Z = pi/100*trapz(Y)

produce

Z = 1.9998

Example 2

A nonuniformly spaced example is generated by

X = sort(rand(1,101)*pi); Y = sin(X); Z = trapz(X,Y);

The result is not as accurate as the uniformly spaced grid. One random sample produced

Z = 1.9984

Example 3

This example uses two complex inputs:

```
z = exp(1i*pi*(0:100)/100);
trapz(z, 1./z)
ans =
    0.0000 + 3.1411i
```


See Also cumsum, cumtrapz

Purpose	Lay out tree or forest
Syntax	[x,y] = treelayout(parent,post) [x,y,h,s] = treelayout(parent,post)
Description	<pre>[x,y] = treelayout(parent,post) lays out a tree or a forest. parent is the vector of parent pointers, with 0 for a root. post is an optional postorder permutation on the tree nodes. If you omit post, treelayout computes it. x and y are vectors of coordinates in the unit square at which to lay out the nodes of the tree to make a nice picture.</pre>
	[x,y,h,s] = treelayout(parent,post) also returns the height of the tree h and the number of vertices s in the top-level separator.
See Also	etree, treeplot, etreeplot, symbfact

treeplot

Purpose	Plot picture of tree
Syntax	<pre>treeplot(p) treeplot(p,nodeSpec,edgeSpec)</pre>
Description	treeplot(p) plots a picture of a tree given a vector of parent pointers, with $p(i) = 0$ for a root.
	treeplot(p,nodeSpec,edgeSpec) allows optional parameters nodeSpec and edgeSpec to set the node or edge color, marker, and linestyle. Use '' to omit one or both.
Examples	To plot a tree with 12 nodes, call treeplot with a 12-element input vector. The index of each element in the vector is shown adjacent to each

vector. The index of each element in the vector is shown adjacent to each node in the figure below. (These indices are shown only for the point of illustrating the example; they are not part of the treeplot output.)



To generate this plot, set the value of each element in the nodes vector to the index of its parent, (setting the parent of the root node to zero).

The node marked 1 in the figure is represented by nodes(1) in the input vector, and because this is the root node which has a parent of zero, you set its value to zero:

nodes(1) = 0; % Root node

nodes(2) and nodes(8) are children of nodes(1), so set these elements of the input vector to 1:

nodes(2) = 1; nodes(8) = 1;

nodes(5:7) are children of nodes(4), so set these elements to 4:

nodes(5) = 4; nodes(6) = 4; nodes(7) = 4;

Continue in this manner until each element of the vector identifies its parent. For the plot shown above, the nodes vector now looks like this:

nodes = [0 1 2 2 4 4 4 1 8 8 10 10];

Now call treeplot to generate the plot:

treeplot(nodes)


See Also etree, etreeplot, treelayout

Purpose	Lower triangular part of matrix
---------	---------------------------------

Syntax L = tril(X)L = tril(X,k)

Description L = tril(X) returns the lower triangular part of X.

L = tril(X,k) returns the elements on and below the kth diagonal of X. k = 0 is the main diagonal, k > 0 is above the main diagonal, and k < 0 is below the main diagonal.



Examples	tri
	ans

tril(ones	(4,4)	,-1)
-----------	-------	------

0	0	0
0	0	0
1	0	0
1	1	0
	0 1	0 0 1 0


See Also

diag, triu

Purpose	Triangular mesh plot
Folbose	Triangular mesh plot
Syntax	<pre>trimesh(Tri,X,Y,Z,C) trimesh(Tri,X,Y,Z) trimesh(Tri, X, Y) trimesh(TR) trimesh('PropertyName',PropertyValue) h = trimesh()</pre>
Description	trimesh(Tri,X,Y,Z,C) displays triangles defined in the <i>m</i> -by-3 face matrix Tri as a mesh. Each row of Tri defines a single triangular face by indexing into the vectors or matrices that contain the X, Y, and Z vertices. The edge color is defined by the vector C.
	trimesh(Tri,X,Y,Z) uses $C = Z$ so color is proportional to surface height.
	trimesh(Tri, X, Y) displays the triangles in a 2-D plot.
	trimesh(TR) displays the triangles in a TriRep triangulation representation.
	trimesh(' <i>PropertyName</i> ', PropertyValue) specifies additional patch property names and values for the patch graphics object created by the function.
	h = trimesh() returns a handle to the displayed triangles.
Example	Create vertex vectors and a face matrix, then create a triangular mesh plot.
	[x,y]=meshgrid(1:15,1:15); tri = delaunay(x,y); z = peaks(15);

trimesh(tri,x,y,z)

trimesh



If the surface is already a triangulation representation it may be plotted as follows:

tr = TriRep(tri, x(:), y(:), z(:));
trimesh(tr)


See Also patch, trisurf, delaunay, DelaunayTri, TriRep

Purpose	Numerically evaluate triple integral	
Syntax	triplequad(fun,xmin,xmax,ymin,ymax,zmin,zmax) triplequad(fun,xmin,xmax,ymin,ymax,zmin,zmax,tol) triplequad(fun,xmin,xmax,ymin,ymax,zmin,zmax,tol,method)	
Description	<pre>triplequad(fun,xmin,xmax,ymin,ymax,zmin,zmax) evaluates the triple integral fun(x,y,z) over the three dimensional rectangular region xmin <= x <= xmax, ymin <= y <= ymax, zmin <= z <= zmax fun is a function handle. See "Function Handles" in the MATLAB Programming documentation for more information.fun(x,y,z) must accept a vector x and scalars y and z, and return a vector of values of the integrand.</pre>	
	"Parameterizing Functions", in the MATLAB Mathematics documentation, explains how to provide additional parameters to the function fun, if necessary.	
	<pre>triplequad(fun,xmin,xmax,ymin,ymax,zmin,zmax,tol) uses a tolerance tol instead of the default, which is 1.0e-6.</pre>	
	triplequad(fun,xmin,xmax,ymin,ymax,zmin,zmax,tol,method) uses the quadrature function specified as method, instead of the default quad. Valid values for method are @quadl or the function handle of a user-defined quadrature method that has the same calling sequence as quad and quadl.	
Examples	Pass M-file function handle @integrnd to triplequad:P	
	<pre>Q = triplequad(@integrnd,0,pi,0,1,-1,1);</pre>	
	where the M-file integrnd.m is	
	<pre>function f = integrnd(x,y,z) f = y*sin(x)+z*cos(x);</pre>	
	Pass anonymous function handle F to triplequad:	
	F = @(x,y,z)y*sin(x)+z*cos(x);	

	Q = triplequad(F,0,pi,0,1,-1,1);
	This example integrates $y*sin(x)+z*cos(x)$ over the region 0 <= x <= pi, 0 <= y <= 1, -1 <= z <= 1. Note that the integrand can be evaluated with a vector x and scalars y and z.
See Also	dblquad, quad2d, quad, quadgk, quadl, function handle (@), "Anonymous Functions"

Purpose	2-D triangular plot
Syntax	triplot(TRI,x,y) triplot(TRI,x,y,color) h = triplot() triplot(,'param','value','param','value')
Description	triplot(TRI,x,y) displays the triangles defined in the m-by-3 matrix TRI. A row of TRI contains indices into the vectors x and y that define a single triangle. The default line color is blue.
	<pre>triplot(TRI,x,y,color) uses the string color as the line color. color can also be a line specification. See ColorSpec for a list of valid color strings. See LineSpec for information about line specifications.</pre>
	h = triplot() returns a vector of handles to the displayed triangles.
	triplot(, 'param', 'value', 'param', 'value') allows additional line property name/property value pairs to be used when creating the plot. See Line Properties for information about the available properties.
Examples	<pre>Plot a Delaunay triangulation for 10 randomly generated points. X = rand(10,2); dt = DelaunayTri(X); triplot(dt)</pre>

triplot



Plot the Delaunay triangulation in face-vertex format.

tri = dt(:,:); triplot(tri, X(:,1), X(:,2));

See Also


DelaunayTri, delaunay, trimesh, trisurf

Purpose	Triangulation representation	
Description	TriRep provides topological and geometric queries for triangulations in 2-D and 3-D space. For example, for triangular meshes you can query triangles attached to a vertex, triangles that share an edge, neighbor information, circumcenters, or other features. You can create a TriRep directly using existing triangulation data. Alternatively, you can create a Delaunay triangulation, via DelaunayTri, which provides access to the TriRep functionality.	
Construction	TriRep	Triangulation representation
Methods	baryToCart	Converts point coordinates from barycentric to Cartesian
	cartToBary	Convert point coordinates from cartesian to barycentric
	circumcenters	Circumcenters of specified simplices
	edgeAttachments	Simplices attached to specified edges
	edges	Triangulation edges
	faceNormals	Unit normals to specified triangles
	featureEdges	Sharp edges of surface triangulation
	freeBoundary	Facets referenced by only one simplex
	incenters	Incenters of specified simplices
	isEdge	Test if vertices are joined by edge

neighbors	Simplex neighbor information
size	Size of triangulation matrix
vertexAttachments	Return simplices attached to specified vertices


Duonoution		
Properties	Х	Coordinates of the points in the triangulation
	Triangulation	Triangulation data structure
Copy Semantics	Value. To learn how this affects your use of the class, see Comparing Handle and Value Classes in the MATLAB Object-Oriented Programming documentation.	
Indexing	TriRep objects support indexing into the triangulation using parentheses (). The syntax is the same as for arrays.	
Examples	Load a 2-D triangulation and use the TriRep constructor to build an array of the free boundary edges:	
	load trimesh2d	
	<pre>This loads triangulation tri and vertex coordinates x, y: trep = TriRep(tri, x,y); fe = freeBoundary(trep)'; triplot(trep);</pre>	

TriRep class



You can add the free edges fe to the plot:

```
hold on;
plot(x(fe), y(fe), 'r','LineWidth',2);
hold off;
axis([-50 350 -50 350]);
axis equal;
```



See Also

DelaunayTri class TriScatteredInterp class

Purpose	Triangulation representation	
Syntax	TR = TriRep(TRI, X, Y) TR = TriRep(TRI, X, Y, Z) TR = TriRep(TRI, X)	
Description	TR = TriRep(TRI, X, Y) creates a 2-D triangulation representation from the triangulation matrix TRI and the vertex coordinates (X, Y). TRI is an m-by-3 matrix that defines the triangulation in face-vertex format, where m is the number of triangles. Each row of TRI is a triangle defined by indices into the column vector of vertex coordinates (X, Y).	
	TR = TriRep(TRI, X, Y, Z) creates a 3-D triangulation representation from the triangulation matrix TRI and the vertex coordinates (X, Y, Z). TRI is an m-by-3 or m-by-4 matrix that defines the triangulation in simplex-vertex format, where where m is the number of simplices; triangles or tetrahedra in this case. Each row of TRI is a simplex defined by indices into the column vector of vertex coordinates (X, Y, Z).	
	TR = TriRep(TRI, X) creates a triangulation representation from the triangulation matrix TRI and the vertex coordinates X. TRI is an m-by-n matrix that defines the triangulation in simplex-vertex format, where m is the number of simplices and n is the number of vertices per simplex. Each row of TRI is a simplex defined by indices into the array of vertex coordinates X. X is anmpts-by-ndim matrix where mpts is the number of points and ndim is the dimension of the space where the points reside, where $2 \le n\dim \le 3$.	
Examples	Load a 3-D tetrahedral triangulation compute the free boundary. First, load triangulation tet and vertex coordinates X. load tetmesh	
	<pre>Create the triangulation representation and compute the free boundary. trep = TriRep(tet, X); [tri, Xb] = freeBoundary(trep);</pre>	

See Also TriScatteredInterp "Interpolation"— A guide to MATLAB's object-oriented and functional capabilities for computational geometry.

Purpose Interpolat	e scattered data
---------------------------	------------------

Description A scattered data set defined by locations X and corresponding values V can be interpolated using a Delaunay triangulation of X. This produces a surface of the form V = F(X). The surface can be evaluated at any query location QX, using QV = F(QX), where QX lies within the convex hull of X. The interpolant F always goes through the data points specified by the sample.

Definitions The *Delaunay triangulation* of a set of points is a triangulation such that the unique circle circumscribed about each triangle contains no other points in the set. The *convex hull* of a set of points is the smallest convex set containing all points of the original set. These definitions extend naturally to higher dimensions.

Construction	TriScatteredInterp
--------------	--------------------

Properties

Х	Defines locations of scattered data points in 2-D or 3-D space.	
V	Defines value associated with each data point.	
Method	Defines method used to interpolate the data .	
	natural	Natural neighbor interpolation
	linear	Linear interpolation (default)
	nearest	Nearest neighbor interpolation

Interpolate scattered data

Copy Semantics

Value. To learn how this affects your use of the class, see Comparing Handle and Value Classes in the MATLAB Object-Oriented Programming documentation.

Examples	Create a data set:
----------	--------------------


x = rand(100,1)*4-2; y = rand(100,1)*4-2; z = x.*exp(-x.^2-y.^2);

Construct the interpolant:

F = TriScatteredInterp(x,y,z);

Evaluate the interpolant at the locations (qx, qy). The corresponding value at these locations is qz:

```
ti = -2:.25:2;
[qx,qy] = meshgrid(ti,ti);
qz = F(qx,qy);
mesh(qx,qy,qz);
hold on;
plot3(x,y,z,'o');
```



DelaunayTri interp1 interp2 interp3 meshgrid


TriScatteredInterp

Purpose	Interpolate scattered data
Syntax	<pre>F = TriScatteredInterp() F = TriScatteredInterp(X, V) F = TriScatteredInterp(X, Y, V) F = TriScatteredInterp(X, Y, Z, V) F = TriScatteredInterp(DT, V) F = TriScatteredInterp(, method)</pre>
Description	F = TriScatteredInterp() creates an empty scattered data interpolant. This can subsequently be initialized with sample data points and values (Xdata, Vdata) via F.X = Xdata and F.V = Vdata.
	F = TriScatteredInterp(X, V) creates an interpolant that fits a surface of the form $V = F(X)$ to the scattered data in (X, V). X is a matrix of size mpts-by-ndim, where mpts is the number of points and ndim is the dimension of the space where the points reside, ndim >= 2. The column vector V defines the values at X, where the length of V equals mpts.
	F = TriScatteredInterp(X, Y, V) and $F = TriScatteredInterp(X, Y, Z, V)$ allow the data point locations to be specified in alternative column vector format when working in 2-D and 3-D.
	F = TriScatteredInterp(DT, V) uses the specified DelaunayTri object DT as a basis for computing the interpolant. The matrix DT.X is of size mpts-by-ndim, where mpts is the number of points and ndim is the dimension of the space where the points reside, 2 <= ndim <= 3. V is a column vector that defines the values at DT.X, where the length of V equals mpts.
	F = TriScatteredInterp(, method) allows selection of the technique method used to interpolate the data.

Input Arguments	X	Matrix of size mpts-by-ndim, where mpts is the number of points and ndim is the dimension of the space where the points reside.	
	V	Column vector that defines the values at X, where the length of V equals mpts.	
	DT	Delaunay triangu	lation of the scattered data
	method	natural	Natural neighbor interpolation
		linear	Linear interpolation (default)
		nearest	Nearest-neighbor interpolation
Output Arguments	F		olant that fits a surface of) to the scattered data.
Evaluation		nterpolant, express the st), or V=F(x,y,z).	catement in Monge's form
Definitions		ircle circumscribed about	nts is a triangulation such each triangle contains no
Examples	Create a data set	:	
	<pre>x = rand(100,1)*4-2; y = rand(100,1)*4-2; z = x.*exp(-x.^2-y.^2);</pre>		
	Construct the int	erpolant:	
	F = TriScatt	eredInterp(x,y,z);	

Evaluate the interpolant at the locations (qx, qy). The corresponding value at these locations is qz .


ti = -2:.25:2; [qx,qy] = meshgrid(ti,ti); qz = F(qx,qy); mesh(qx,qy,qz); hold on; plot3(x,y,z,'o');



See Also

DelaunayTri interp1 interp2 interp3 meshgrid

Purpose	Triangular surface plot
Syntax	<pre>trisurf(Tri,X,Y,Z,C) trisurf(Tri,X,Y,Z) trisurf(tr) trisurf('PropertyName',PropertyValue) h = trisurf()</pre>
Description	trisurf(Tri,X,Y,Z,C) displays triangles defined in the m -by-3 face matrix Tri as a surface. Each row of Tri defines a single triangular face by indexing into the vectors or matrices that contain the X, Y, and Z vertices. The color is defined by the vector C.
	trisurf(Tri,X,Y,Z) uses C=Z so color is proportional to surface height.
	<pre>trisurf(tr) displays the triangles in a TriRep triangulation representation. It uses C = TR.X(:,3) so surface color is proportional to height.</pre>
	trisurf(' <i>PropertyName</i> ', PropertyValue) specifies additional patch property names and values for the patch graphics object created by the function.
	h = trisurf() returns a patch handle.
Example	Create vertex vectors and a face matrix, then create a triangular surface plot.
	<pre>[x,y]=meshgrid(1:15,1:15); tri = delaunay(x,y); z = peaks(15); trisurf(tri,x,y,z)</pre>
	If the surface is in the form of a TriRep triangulation representation, plot it as follows:
	tr = TriRep(tri, x(:), y(:), z(:)); trisurf(tr)




See Also patch, surf, tetramesh, trimesh, triplot, delaunay, TriRep, DelaunayTri

"Surface and Mesh Creation" on page 1-107 for related functions

- Purpose Upper triangular part of matrix
- **Syntax** U = triu(X)U = triu(X,k)

Description U = triu(X) returns the upper triangular part of X.

- U = triu(X,k) returns the element on and above the kth diagonal of X. $k\,$ = $\,0$ is the main diagonal, $k\,$ > $\,0$ is above the main diagonal, and k
- < 0 is below the main diagonal.



1

1

1

1

Examples	imples triu(ones(4,4),-1))	
	ans =			
	1	1	1	
	1	1	1	
	0	1	1	
	0	0	1	

See Also

diag, tril

true

Purpose	Logical 1 (true)
Syntax	true true(n) true(m, n) true(m, n, p,) true(size(A))
Description	true is shorthand for logical 1.
	true(n) is an n-by-n matrix of logical ones.
	<pre>true(m, n) or true([m, n]) is an m-by-n matrix of logical ones.</pre>
	true(m, n, p,) or true([m n p]) is an m-by-n-by-p-by array of logical ones.
	Note The size inputs m, n, p, should be nonnegative integers. Negative integers are treated as 0.
	true(size(A)) is an array of logical ones that is the same size as array A.
Remarks	<pre>true(n) is much faster and more memory efficient than logical(ones(n)).</pre>
See Also	false, logical

Purpose	Execute statements and catch resulting errors
Syntax	<pre>try program statements : catch exception error-handling statements : end</pre>
Description	try plus one or more <i>program statements</i> that follow it make up the first part of a <i>try-catch</i> statement. This part is often referred to as a <i>try block</i> , and is always immediately followed by a <i>catch block</i> . The catch block consists of the catch <i>exception</i> command followed by one or more <i>error-handling statements</i> . The try-catch statement is used in detecting and handling errors. It enables you to implement your own error handling for selected segments of your program code.
	The try block begins with the try keyword and ends just before the catch keyword. It contains one or more commands for which special error handling is required by your program. Any error detected while executing statements in the try block immediately turns program control over to the catch block. Code in the catch block provides error handling that specifically addresses errors that might originate from statements in the preceding try block.
	Both the try and catch blocks may contain additional try-catch statements nested within them.
	See "The try-catch Statement" in the Programming Fundamentals documentation for more information.
Remarks	Specifying the try, catch, and end commands, as well as the commands that make up the try and catch blocks, on separate lines is recommended. If you combine any of these components on the same line, separate them with commas.

Examples Example 1

The first part of this example attempts to vertically concatenate two matrices that have an unequal number of columns:

```
A = rand(5,3); B = rand(4,5);
C = [A; B];
??? Error using ==> vertcat
CAT arguments dimensions are not consistent.
```

Using a try-catch statement, you can provide more information about what went wrong:

```
function C = catchErr(A, B);
try
  C = [A; B];
catch exception
   % Branch here on an exception. If problem is a
   % dimension mismatch, throw the appropriate error.
   if (strcmp(exception.identifier, ...
   'MATLAB:catenate:dimensionMismatch'))
      msg = longMsg(size(A,2), size(B,2));
      error('MATLAB:myFunction:Dimensionality', msg);
   % Otherwise, just let the error propagate.
   else
      throw(exception);
   end
       % end try-catch
end
% Subfunction to put longish message together.
function msg = longMsg(Acols, Bcols)
msg = sprintf('%s', ...
   'Dimension mismatch occured: First argument has ', ...
   num2str(Acols), ' columns while second argument has ', ...
   num2str(Bcols), ' columns.');
```

Running the program displays the following message:

```
catchErr(A, B)
??? Error using ==> catchErr at 8
Dimension mismatch occured: First argument has 3 columns
while second argument has 5 columns.
```

Example 2

The catch block in this example checks to see if the specified file could not be found. If this is the case, the program allows for the possibility that a common variation of the filename extension (e.g., jpeg instead of jpg) was used by retrying the operation with a modified extension. This is done using a try-catch statement that is nested within the original try-catch.

```
function d in = read image(filename)
[path name ext] = fileparts(filename);
try
  fid = fopen(filename, 'r');
   d in = fread(fid);
catch exception
  % Did the read fail because the file could not be found?
   if ~exist(filename, 'file')
      % Yes. Try modifying the filename extension.
      switch ext
      case '.ipg'
                     % Change jpg to jpeg
          altFilename = strrep(filename, '.jpg', '.jpeg')
      case '.jpeg'
                     % Change jpeg to jpg
          altFilename = strrep(filename, '.jpeg', '.jpg')
      case '.tif'
                     % Change tif to tiff
          altFilename = strrep(filename, '.tif', '.tiff')
                     % Change tiff to tif
      case '.tiff'
          altFilename = strrep(filename, '.tiff', '.tif')
      otherwise
         rethrow(exception);
      end
```

```
% Try again, with modifed filename.
try
fid = fopen(altFilename, 'r');
d_in = fread(fid);
catch
rethrow(exception)
end
end
end
```

See Also catch, error, assert, MException, throw(MException), rethrow(MException), throwAsCaller(MException), addCause(MException), getReport(MException), last(MException)

Purpose	Create tscollection object
Syntax	<pre>tsc = tscollection(TimeSeries) tsc = tscollection(Time) tsc = tscollection(Time,TimeSeries,'Parameter',Value,)</pre>
Description	tsc = tscollection(TimeSeries) creates a tscollection object tsc with one or more timeseries objects already in the MATLAB workspace. The argument TimeSeries can be a
	• Single timeseries object
	• Cell array of timeseries objects
	tsc = tscollection(Time) creates an empty tscollection object with the time vector Time. When time values are date strings, you must specify Time as a cell array of date strings.
	<pre>tsc = tscollection(Time,TimeSeries, 'Parameter',Value,) creates a tscollection object with optional parameter-value pairs you enter after the Time and TimeSeries arguments. You can specify the following parameter:</pre>
	ullet Name — String that specifies the name of this <code>tscollection</code> object
Remarks	Definition: Time Series Collection
	A time series collection object is a MATLAB variable that groups several time series with a common time vector. The time series that you include in the collection are called members of this collection.
	Properties of Time Series Collection Objects
	This table lists the properties of the tscollection object. You can specify the Time, TimeSeries, and Name properties as input arguments

in the constructor.

Property	Description
Name	tscollection name as a string. This can differ from th tscollection name in the MATLAB workspace.
Time	When TimeInfo.StartDate is empty, values are measured relative to 0. When TimeInfo.StartDate is defined, values represent date strings measured relative to the StartDate.
	The length of Time must be the same as the first or the last dimension of Data for each collection .
TimeInfo	Contains fields for contextual information about ${\tt Time}:$
	• Units — Time units with any of the following values 'weeks', 'days', 'hours', 'minutes', 'seconds', 'milliseconds', 'microseconds', 'nanoseconds'
	• Start — Start time
	• End — End time (read only)
	• Increment — Interval between subsequent time values. NaN when times are not uniformly sampled.
	• Length — Length of the time vector (read only)
	• Format — String defining the date string display format. See datestr.
	• StartDate — Date string defining the reference date See setabstime (tscollection).
	• UserData — Any additional user-defined information

1 Import the sample data.

load count.dat

Examples

2 Create three timeseries objects to store each set of data:

```
count1 = timeseries(count(:,1),1:24,'name', 'ts1');
count2 = timeseries(count(:,2),1:24,'name', 'ts2');
```

3 Create a tscollection object named tsc and add to it two out of three time series already in the MATLAB workspace, by using the following syntax:

```
tsc = tscollection({count1 count2}, 'name', 'tsc')
```

See Also addts, datestr, setabstime (tscollection), timeseries, tsprops

tsdata.event

Purpose	Construct event object for timeseries object
Syntax	e = tsdata.event(Name,Time) e = tsdata.event(Name,Time,'Datenum')
Description	e = tsdata.event(Name,Time) creates an event object with the specified Name that occurs at the time Time. Time can either be a real value or a date string.
	<pre>e = tsdata.event(Name,Time,'Datenum') uses 'Datenum' to indicate that the Time value is a serial date number generated by the datenum function. The Time value is converted to a date string after the event is created.</pre>
Remarks	You add events by using the addevent method.
	Fields of the tsdata.event object include the following:
	• EventData — MATLAB array that stores any user-defined information about the event
	• Name — String that specifies the name of the event
	• Time — Time value when this event occurs, specified as a real number
	• Units — Time units
	• StartDate — A reference date, specified in MATLAB datestr format. StartDate is empty when you have a numerical (non-date-string) time vector.

Purpose	Search for enclosing Delaunay triangle tsearch will be removed in a future release. Use DelaunayTri/pointLocation instead.
Syntax	T = tsearch(x,y,TRI,xi,yi)
Description	T = tsearch(x,y,TRI,xi,yi) returns an index into the rows of TRI for each point in xi, yi. The tsearch command returns NaN for all points outside the convex hull. Requires a triangulation TRI of the points x,y obtained from delaunay.
See Also	DelaunayTri, delaunay, delaunayn, tsearchn

tsearchn

Purpose	N-D closest simplex search
Syntax	t = tsearchn(X,TES,XI) [t,P] = tsearchn(X,TES,XI)
Description	<pre>t = tsearchn(X,TES,XI) returns the indices t of the enclosing simplex of the Delaunay tessellation TES for each point in XI. X is an m-by-n matrix, representing m points in N-dimensional space. XI is a p-by-n matrix, representing p points in N-dimensional space. tsearchn returns NaN for all points outside the convex hull of X. tsearchn requires a tessellation TES of the points X obtained from delaunayn.</pre>
	[t,P] = tsearchn(X,TES,XI) also returns the barycentric coordinate P of XI in the simplex TES. P is a p-by-n+1 matrix. Each row of P is the Barycentric coordinate of the corresponding point in XI. It is useful for interpolation.
Algorithm	tsearchn is based on Qhull [1]. For information about Qhull, see http://www.qhull.org/. For copyright information, see http://www.qhull.org/COPYING.txt.
See Also	DelaunayTri, tsearch
Reference	[1] Barber, C. B., D.P. Dobkin, and H.T. Huhdanpaa, "The Quickhull Algorithm for Convex Hulls," <i>ACM Transactions on Mathematical</i> <i>Software</i> , Vol. 22, No. 4, Dec. 1996, p. 469–483.

Purpose	Help on timeseries object properties
Syntax	help timeseries/tsprops
Description	help timeseries/tsprops lists the properties of the timeseries object and briefly describes each property.

Time Series Object Properties

Property	Description
Data	Time-series data, where each data sample corresponds to a specific time.
	The data can be a scalar, a vector, or a multidimensional array. Either the first or last dimension of the data must be aligned with Time.
	By default, NaNs are used to represent missing or unspecified data. Set the TreatNaNasMissing property to determine how missing data is treated in calculations.
DataInfo	Contains fields for storing contextual information about Data:
	• Unit — String that specifies data units
	 Interpolation — A tsdata.interpolation object that specifies the interpolation method for this time series.
	Fields of the tsdata.interpolation object include:
	 Fhandle — Function handle to a user-defined interpolation function
	 Name — String that specifies the name of the interpolation method. Predefined methods include 'linear' and 'zoh' (zero-order hold). 'linear' is the default.
	• UserData — Any user-defined information entered as a string

Property	Description
Events	An array of tsdata.event objects that stores event information for this time series. You add events by using the addevent method.
	Fields of the tsdata.event object include the following:
	• EventData — Any user-defined information about the event
	• Name — String that specifies the name of the event
	• Time — Time value when this event occurs, specified as a real number or a date string
	• Units — Time units
	• StartDate — A reference date specified in MATLAB date-string format. StartDate is empty when you have a numerical (non-date-string) time vector.
IsTimeFirst	Logical value (true or false) specifies whether the first or last dimension of the Data array is aligned with the time vector.
	You can set this property when the Data array is square and it is ambiguous which dimension is aligned with time. By default, the first Data dimension that matches the length of the time vector is aligned with the time vector.
	When you set this property to:
	 true — The first dimension of the data array is aligned with the time vector. For example: ts=timeseries(rand(3,3),1:3, 'IsTimeFirst',true);
	 false — The last dimension of the data array is aligned with the time vector. For example: ts=timeseries(rand(3,3),1:3, 'IsTimeFirst',false);

Property	Description
	After a time series is created, this property is read only.
Name	Time-series name entered as a string. This name can differ from the name of the time-series variable in the MATLAB workspace.
Quality	An integer vector or array containing values -128 to 127 that specifies the quality in terms of codes defined by QualityInfo.Code.
	When Quality is a vector, it must have the same length as the time vector. In this case, each Quality value applies to a corresponding data sample.
	When Quality is an array, it must have the same size as the data array. In this case, each Quality value applies to the corresponding value of the data array.
QualityInfo	Provides a lookup table that converts numerical Quality codes to readable descriptions. QualityInfo fields include the following:
	• Code — Integer vector containing values -128 to 127 that define the "dictionary" of quality codes, which you can assign to each Data value by using the Quality property
	• Description — Cell vector of strings, where each element provides a readable description of the associated quality Code
	ullet UserData — Stores any additional user-defined information
	Lengths of Code and Description must match.

Property	Description
Time	Array of time values.
	When TimeInfo.StartDate is empty, the numerical Time values are measured relative to 0 in specified units. When TimeInfo.StartDate is defined, the time values are date strings measured relative to the StartDate in specified units.
	The length of Time must be the same as either the first or the last dimension of Data.
TimeInfo	Uses the following fields for storing contextual information about Time:
	 Units — Time units can have any of following values: 'weeks', 'days', 'hours', 'minutes', 'seconds', 'milliseconds', 'microseconds', or 'nanoseconds'
	• Start — Start time
	• End — End time (read only)
	• Increment — Interval between two subsequent time values
	 Length — Length of the time vector (read only)
	• Format — String defining the date string display format. See the MATLAB datestr function reference page for more information.
	• StartDate — Date string defining the reference date. See the MATLAB setabstime (timeseries) function reference page for more information.
	$\bullet \ {\tt UserData} - {\tt Stores} \ {\tt any} \ {\tt additional} \ {\tt user-defined} \ {\tt information}$

Property	Description
TreatNaNasMissing	Logical value that specifies how to treat NaN values in Data:
	• true — (Default) Treat all NaN values as missing data except during statistical calculations.
	• false — Include NaN values in statistical calculations, in which case NaN values are propagated to the result.

See Also datestr, get (timeseries), set (timeseries), setabstime (timeseries)

tstool

Purpose	Open Time Series Tools GUI
Syntax	tstool tstool(ts) tstool(tsc) tstool(sldata) tstool(ModelDataLogs,'replace')
Description	tstool starts the Time Series Tools GUI without loading any data.
	tstool(ts) starts the Time Series Tools GUI and loads the time-series object ts from the MATLAB workspace.
	tstool(tsc) starts the Time Series Tools GUI and loads the time-series collection object tsc from the MATLAB workspace.
	tstool(sldata) starts the Time Series Tools GUI and loads the logged-signal data sldata from a Simulink model. If a Simulink logged signal Name property contains a /, the entire logged signal, including all levels of the signal hierarchy, is not imported into Time Series Tools.
	tstool(ModelDataLogs, 'replace') replaces the logged-signal data object ModelDataLogs in the Time Series Tools GUI with an updated logged signal after you rerun the Simulink model. Use this command to update the ModelDataLogs object in the Time Series Tools GUI if you change the model or the logged-signal data settings.
See Also	timeseries, tscollection

Purpose	Display contents of file	
Syntax	type('filename') type filename	
Description	type('filename') displays the contents of the specified file in the MATLAB Command Window. Use the full path for filename, or use a MATLAB relative partial path.	
	If you do not specify a file extension and there is no filename file without an extension, the type function adds the .m extension by default. The type function checks the directories specified in the MATLAB search path, which makes it convenient for listing the contents of files on the screen. Use type with more on to see the listing one screen at a time.	
	type filename is the command form of the syntax.	
Examples	type('foo.bar') lists the contents of the file foo.bar. type foo lists the contents of the file foo. If foo does not exist, type foo lists the contents of the file foo.m.	
See Also	cd, dbtype, delete, dir, more, path, what, who	

typecast

Purpose	Convert data types without changing underlying data
Syntax	Y = typecast(X, type)
Description	Y = typecast(X, type) converts a numeric value in X to the data type specified by type. Input X must be a full, noncomplex, numeric scalar or vector. The type input is a string set to one of the following: 'uint8', 'int8', 'uint16', 'int16', 'uint32', 'int32', 'uint64', 'int64', 'single', or 'double'.
	typecast is different from the MATLAB cast function in that it does not alter the input data. typecast always returns the same number of

not alter the input data. typecast always returns the same number of bytes in the output Y as were in the input X. For example, casting the 16-bit integer 1000 to uint8 with typecast returns the full 16 bits in two 8-bit segments (3 and 232) thus keeping its original value (3*256 + 232 = 1000). The cast function, on the other hand, truncates the input value to 255.

The output of typecast can be formatted differently depending on what system you use it on. Some computer systems store data starting with its most significant byte (an ordering called *big-endian*), while others start with the least significant byte (called *little-endian*).

Note MATLAB issues an error if X contains fewer values than are needed to make an output value.

Examples Example 1

This example converts between data types of the same size:

```
typecast(uint8(255), 'int8')
ans =
    -1
typecast(int16(-1), 'uint16')
ans =
```

65535

Example 2

Set X to a 1-by-3 vector of 32-bit integers, then cast it to an 8-bit integer type:

```
X = uint32([1 255 256])
X =
1 255 256
```

Running this on a little-endian system produces the following results. Each 32-bit value is divided up into four 8-bit segments:

```
Y = typecast(X, 'uint8')
Y =
1 0 0 0 255 0 0 0 1 0 0
```

The third element of X, 256, exceeds the 8 bits that it is being converted to in Y(9) and thus overflows to Y(10):

Y(9:12) ans = 0 1 0 0

Note that length(Y) is equal to 4.*length(X). Also note the difference between the output of typecast versus that of cast:

```
Z = cast(X, 'uint8')
Z =
1 255 255
```

Example 3

This example casts a smaller data type (uint8) into a larger one (uint16). Displaying the numbers in hexadecimal format makes it easier to see just how the data is being rearranged:

format hex X = uint8([44 55 66 77]) X =

typecast

2c 37 42 4d

The first typecast is done on a big-endian system. The four 8-bit segments of the input data are combined to produce two 16-bit segments:

```
Y = typecast(X, 'uint16')
Y =
2c37 424d
```

The second is done on a little-endian system. Note the difference in byte ordering:

```
Y = typecast(X, 'uint16')
Y =
372c 4d42
```

You can format the little-endian output into big-endian (and vice versa) using the swapbytes function:

```
Y = swapbytes(typecast(X, 'uint16'))
Y =
2c37 424d
```

Example 4

This example attempts to make a 32-bit value from a vector of three 8-bit values. MATLAB issues an error because there are an insufficient number of bytes in the input:

format hex
typecast(uint8([120 86 52]), 'uint32')
??? Too few input values to make output type.
Error in ==> typecast at 29
out = typecastc(in, datatype);

Repeat the example, but with a vector of four 8-bit values, and it returns the expected answer:

typecast(uint8([120 86 52 18]), 'uint32') ans = 12345678

See Also cast, class, swapbytes

uibuttongroup

Purpose	Create container object to exclusively manage radio buttons and toggle buttons
Syntax	uibuttongroup(' <i>PropertyName1</i> ',Value1,' <i>PropertyName2</i> ',Value2,) handle = uibuttongroup()
Description	A uibuttongroup groups components and manages exclusive selection behavior for radio buttons and toggle buttons that it contains. It can also contain other user interface controls, axes, uipanels, and uibuttongroups. It cannot contain ActiveX controls.
	uibuttongroup(' <i>PropertyName1</i> ',Value1,' <i>PropertyName2</i> ',Value2,) creates a visible container component in the current figure window. This component manages exclusive selection behavior for uicontrols of style radiobutton and togglebutton.
	handle = uibuttongroup() creates a uibuttongroup object and returns a handle to it in handle.
	A uibuttongroup object can have axes, uicontrol, uipanel, and uibuttongroup objects as children. However, only uicontrols of style radiobutton and togglebutton are managed by the component.
	When programming a button group, you do not code callbacks for the individual buttons; instead, use its SelectionChangeFcn callback to manage responses to selections. The following example illustrates how you use uibuttongroup event data to do this.
	For the children of a uibuttongroup object, the Position property is interpreted relative to the button group. If you move the button group, the children automatically move with it and maintain their positions in the button group.
	If you have a button group that contains a set of radio buttons and toggle buttons and you want:
	• An immediate action to occur when a radio button or toggle button is selected, you must include the code to control the radio and toggle buttons in the button group's SelectionChangeFcn callback function,

not in the individual toggle button Callback functions. See the SelectionChangeFcn property and the example on this reference page for more information.

• Another component such as a push button to base its action on the selection, then that component's Callback callback can get the handle of the selected radio button or toggle button from the button group's SelectedObject property.

Use the Parent property to specify the parent as a figure, uipanel, or uibuttongroup. If you do not specify a parent, uibuttongroup adds the button group to the current figure. If no figure exists, one is created.

See the Uibuttongroup Properties reference page for more information.

After creating a uibuttongroup, you can set and query its property values using set and get. Run get(handle) to see a list of properties and their current values. Run set(handle) to see a list of object properties you can set and their legal values.

Remarks

arks If you set the Visible property of a uibuttongroup object to 'off', any child objects it contains (buttons, button groups, etc.) become invisible along with the uibuttongroup panel itself. However, doing this does *not* affect the settings of the Visible property of any of its child objects, even though all of them remain invisible until the button group's visibility is set to 'on'. uipanel components also behave in this manner.

Examples This example creates a uibuttongroup with three radiobuttons. It manages the radiobuttons with the SelectionChangeFcn callback, selcbk.


When you select a new radio button, selcbk displays the uibuttongroup handle on one line, the EventName, OldValue, and NewValue fields of the event data structure on a second line, and the value of the SelectedObject property on a third line.

```
% Create the button group.
h = uibuttongroup('visible','off','Position',[0 0 .2 1]);
```

```
% Create three radio buttons in the button group.
u0 = uicontrol('Style','Radio','String','Option 1',...
'pos',[10 350 100 30],'parent',h,'HandleVisibility','off');
u1 = uicontrol('Style','Radio','String','Option 2',...
'pos',[10 250 100 30],'parent',h,'HandleVisibility','off');
u2 = uicontrol('Style','Radio','String','Option 3',...
'pos',[10 150 100 30],'parent',h,'HandleVisibility','off');
% Initialize some button group properties.
set(h,'SelectionChangeFcn',@selcbk);
set(h,'SelectedObject',[]); % No selection
set(h,'Visible','on');
```

For the SelectionChangeFcn callback, selcbk, the source and event data structure arguments are available only if selcbk is called using a function handle. See SelectionChangeFcn for more information.

```
function selcbk(source,eventdata)
disp(source);
disp([eventdata.EventName,' ',...
    get(eventdata.OldValue,'String'),' ', ...
    get(eventdata.NewValue,'String')]);
disp(get(get(source,'SelectedObject'),'String'));
```



If you click Option 2 with no option selected, the SelectionChangeFcn callback, selcbk, displays:

3.0011

SelectionChanged Option 2 Option 2

If you then click Option 1, the SelectionChangeFcn callback, selcbk, displays:

3.0011

SelectionChanged Option 2 Option 1 Option 1

uibuttongroup

See Also uicontrol, uipanel

Purpose Describe button group properties

Modifying Properties

You can set and query graphics object properties in two ways:

- The Property Inspector is an interactive tool that enables you to see and change object property values. The Property inspector is available from GUIDE, or use the inspect function at the command line.
- The set and get functions enable you to set and query the values of properties.

Uibuttongroup takes its default property values from uipanel. To set a uibuttongroup default property value, set the default for the corresponding uipanel property. Note that you can set no default values for the uibuttongroup SelectedObject and SelectionChangeFcn properties.

For more information about changing the default value of a property see "Setting Default Property Values". For an example, see the CreateFcn property.

Uibuttongroup This section describes all properties useful to uibuttongroup objects and lists valid values. Curly braces {} enclose default values.

Property Name	Description
BackgroundColor	Color of the button group background
BeingDeleted	This object is being deleted
BorderType	Type of border around the button group
BorderWidth	Width of the button group border in pixels
BusyAction	Interruption of other callback routines
ButtonDownFcn	Button-press callback routine
Children	All children of the button group

Property Name	Description
Clipping	Clipping of child axes, panels, and button groups to the button group. Does not affect child user interface controls (uicontrol)
CreateFcn	Callback routine executed during object creation
DeleteFcn	Callback routine executed during object deletion
FontAngle	Title font angle
FontName	Title font name
FontSize	Title font size
FontUnits	Title font units
FontWeight	Title font weight
ForegroundColor	Title font color and color of 2-D border line
HandleVisibility	Handle accessibility from command line and GUIs
HighlightColor	3-D frame highlight color
Interruptible	Callback routine interruption mode
Parent	uibuttongroup object's parent
Position	Button group position relative to parent figure, panel, or button group
ResizeFcn	User-specified resize routine
Selected	Whether object is selected
SelectedObject	Currently selected uicontrol of style radiobutton or togglebutton
SelectionChangeFcn	Callback routine executed when the selected radio button or toggle button changes
SelectionHighlight	Object highlighted when selected

Property Name	Description
ShadowColor	3-D frame shadow color
Тад	User-specified object identifier
Title	Title string
TitlePosition	Location of title string in relation to the button group
Туре	Object class
UIContextMenu	Associate context menu with the button group
Units	Units used to interpret the position vector
UserData	User-specified data
Visible	Button group visibility
	Note Controls the visibility of a uibuttongroup and of its child axes, uibuttongroups. uipanels, and child uicontrols. Setting it does not change their Visible property.

BackgroundColor ColorSpec

Color of the uibuttongroup background. A three-element RGB vector or one of the MATLAB predefined names, specifying the background color. See the **ColorSpec** reference page for more information on specifying color.

BeingDeleted

on | {off} Read Only

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions might not need to perform actions on objects if the objects are going to be deleted, and therefore, can check the object's BeingDeleted property before acting.

BorderType

```
none | {etchedin} | etchedout |
beveledin | beveledout | line
```

Border of the uibuttongroup area. Used to define the button group area graphically. Etched and beveled borders provide a 3-D look. Use the HighlightColor and ShadowColor properties to specify the border color of etched and beveled borders. A line border is 2-D. Use the ForegroundColor property to specify its color.

BorderWidth

integer

Width of the button group border. The width of the button group borders in pixels. The default border width is 1 pixel. 3-D borders wider than 3 may not appear correctly at the corners.

BusyAction

cancel | {queue}

Callback routine interruption. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, the callback associated with the new event uses the value of BusyAction to decide whether or not to attempt to interrupt the executing callback.

• If the value is cancel, the event is discarded and the second callback does not execute.

• If the value is queue, and the Interruptible property of the first callback is on, the second callback is added to the event queue and executes in its turn after the first callback finishes execution.

Note If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. See the Interruptible property for information about controlling a callback's interruptibility.

ButtonDownFcn

string or function handle

Button-press callback routine. A callback routine that executes when you press a mouse button while the pointer is in a 5-pixel wide border around the uibuttongroup. This is useful for implementing actions to interactively modify object properties, such as size and position, when they are clicked on (using the selectmoveresize function, for example).

If you define this routine as a string, the string can be a valid MATLAB expression or the name of a code file. The expression executes in the MATLAB workspace.

Children

vector of handles

Children of the uibuttongroup. A vector containing the handles of all children of the uibuttongroup. Although a uibuttongroup manages only uicontrols of style radiobutton and togglebutton, its children can be axes, uipanels, uibuttongroups, and other uicontrols. You can use this property to reorder the children. Clipping {on} | off

Clipping mode. By default, MATLAB clips a uibuttongroup's child axes, uipanels, and uibuttongroups to the uibuttongroup rectangle. If you set Clipping to off, the axis, uipanel, or uibuttongroup is displayed outside the button group rectangle. This property does not affect child uicontrols which, by default, can display outside the button group rectangle.

CreateFcn

string or function handle

Callback routine executed during object creation. The specified function executes when MATLAB creates a uibuttongroup object. MATLAB sets all property values for the uibuttongroup before executing the CreateFcn callback so these values are available to the callback. Within the function, use gcbo to get the handle of the uibuttongroup being created.

Setting this property on an existing uibuttongroup object has no effect.

To define a default CreateFcn callback for all new uibuttongroups you must define the same default for all uipanels. This default applies unless you override it by specifying a different CreateFcn callback when you call uibuttongroup. For example, the code

```
set(0,'DefaultUipanelCreateFcn','set(gcbo,...
''FontName'',''arial'',''FontSize'',12)')
```

creates a default CreateFcn callback that runs whenever you create a new panel or button group. It sets the default font name and font size of the uipanel or uibuttongroup title.

To override this default and create a button group whose FontName and FontSize properties are set to different values, call uibuttongroup with code similar to

```
hpt = uibuttongroup(...,'CreateFcn','set(gcbo,...
''FontName'',''times'',''FontSize'',14)')
```

Note To override a default CreateFcn callback you must provide a new callback and not just provide different values for the specified properties. This is because the CreateFcn callback runs after the property values are set, and can override property values you have set explicitly in the uibuttongroup call. In the example above, if instead of redefining the CreateFcn property for this uibuttongroup, you had explicitly set FontSize to 14, the default CreateFcn callback would have set FontSize back to the system dependent default.

Do not call copyobj or textwrap (which calls copyobj) inside a CreateFcn. The act of copying the uicontrol object fires the CreateFcn repeatedly, which raises a series of error messages after exceeding the root object's RecursionLimit property.

See "Function Handle Callbacks" for information on how to use function handles to define a callback function.

DeleteFcn

string or function handle

Callback routine executed during object deletion. A callback routine that executes when you delete the uibuttongroup object (e.g., when you issue a delete command or clear the figure containing the uibuttongroup). MATLAB executes the routine before destroying the object's properties so these values are available to the callback routine. The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

FontAngle

{normal} | italic | oblique

Character slant used in the Title. MATLAB uses this property to select a font from those available on your particular system. Setting this property to italic or oblique selects a slanted version of the font, when it is available on your system.

FontName

string

Font family used in the Title. The name of the font in which to display the Title. To display and print properly, this must be a font that your system supports. The default font is system dependent. To eliminate the need to hard code the name of a fixed-width font, which may not display text properly on systems that do not use ASCII character encoding (such as in Japan), set FontName to the string FixedWidth. This string value is case insensitive.

```
set(uicontrol_handle, 'FontName', 'FixedWidth')
```

This then uses the value of the root FixedWidthFontName property, which can be set to the appropriate value for a locale from startup.m in the end user's environment. Setting the root FixedWidthFontName property causes an immediate update of the display to use the new font.

FontSize

integer

Title font size. A number specifying the size of the font in which to display the Title, in units determined by the FontUnits property. The default size is system dependent.

FontUnits

inches | centimeters | normalized |
{points} |pixels

Title font size units. Normalized units interpret FontSize as a fraction of the height of the uibuttongroup. When you resize the uibuttongroup, MATLAB modifies the screen FontSize

accordingly. pixels, inches, centimeters, and points are absolute units (1 point = 1/72 inch).

FontWeight

light | {normal} | demi | bold

Weight of characters in the title. MATLAB uses this property to select a font from those available on your particular system. Setting this property to bold causes MATLAB to use a bold version of the font, when it is available on your system.

ForegroundColor

ColorSpec

Color used for title font and 2-D border line. A three-element RGB vector or one of the MATLAB predefined names, specifying the font or line color. See the ColorSpec reference page for more information on specifying color.

HandleVisibility

{on} | callback | off

Control access to object's handle. This property determines when an object's handle is visible in its parent's list of children. When a handle is not visible in its parent's list of children, it is not returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close. Neither is the handle visible in the parent figure's CurrentObject property. Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

- Handles are always visible when HandleVisibility is on.
- Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from

command-line users, while allowing callback routines to have complete access to object handles.

• Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

Note Uicontrols of style radiobutton and togglebutton that are managed by a uibuttongroup should not be accessed outside the button group. Set the HandleVisibility of such radio buttons and toggle buttons to off or callback to prevent inadvertent access.

You can set the root ShowHiddenHandles property to on to make all handles visible, regardless of their HandleVisibility settings. This does not affect the values of the HandleVisibility properties.

```
HighlightColor
ColorSpec
```

3-D frame highlight color. A three-element RGB vector or one of the MATLAB predefined names, specifying the highlight color. See the ColorSpec reference page for more information on specifying color.

```
Interruptible
```

{on} | off

Callback routine interruption mode. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, that callback attempts to interrupt the first callback. MATLAB processes the callbacks according to these factors:

- The Interruptible property of the object whose callback is executing
- Whether the executing callback contains drawnow, figure, getframe, pause, or waitfor statements
- The BusyAction property of the object whose callback is waiting to execute

If the Interruptible property of the object whose callback is executing is on (the default), the callback can be interrupted. Whenever the callback calls one of the drawnow, figure, getframe, pause, or waitfor functions, the function processes any events in the event queue, including the waiting callback, before performing its defined task.

If the Interruptible property of the object whose callback is executing is off, the callback cannot be interrupted (except by certain callbacks; see the note below). The BusyAction property of the object whose callback is waiting to execute determines what happens to the waiting callback.

Note If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. The interrupting callback starts execution at the next drawnow, figure, getframe, pause, or waitfor statement. A figure's WindowButtonDownFcn callback routine, or an object's ButtonDownFcn or Callback routine is processed according to the rules described above.

Parent

handle

Uibuttongroup parent. The handle of the uibuttongroup's parent figure, uipanel, or uibuttongroup. You can move a uibuttongroup

object to another figure, uipanel, or uibuttongroup by setting this property to the handle of the new parent.

Position

position rectangle

Size and location of uibuttongroup relative to parent. The rectangle defined by this property specifies the size and location of the button group within the parent figure window, uipanel, or uibuttongroup. Specify Position as

[left bottom width height]

left and bottom are the distance from the lower-left corner of the parent object to the lower-left corner of the uibuttongroup object. width and height are the dimensions of the uibuttongroup rectangle, including the title. All measurements are in units specified by the Units property.

ResizeFcn

string or function handle

Resize callback routine. MATLAB executes this callback routine whenever a user resizes the uibuttongroup and the figure Resize property is set to on, or in GUIDE, the **Resize behavior** option is set to Other. You can query the uibuttongroup Position property to determine its new size and position. During execution of the callback routine, the handle to the figure being resized is accessible only through the root CallbackObject property, which you can query using gcbo.

You can use ResizeFcn to maintain a GUI layout that is not directly supported by the MATLAB Position/Units paradigm.

For example, consider a GUI layout that maintains an object at a constant height in pixels and attached to the top of the figure, but always matches the width of the figure. The following ResizeFcn accomplishes this; it keeps the uicontrol whose Tag is 'StatusBar' 20 pixels high, as wide as the figure, and attached to the top of the figure. Note the use of the Tag property to retrieve the uicontrol handle, and the gcbo function to retrieve the figure handle. Also note the defensive programming regarding figure Units, which the callback requires to be in pixels in order to work correctly, but which the callback also restores to their previous value afterwards.

```
u = findobj('Tag','StatusBar');
fig = gcbo;
old_units = get(fig,'Units');
set(fig,'Units','pixels');
figpos = get(fig,'Position');
upos = [0, figpos(4) - 20, figpos(3), 20];
set(u,'Position',upos);
set(fig,'Units',old_units);
```

You can change the figure Position from within the ResizeFcn callback; however, the ResizeFcn is not called again as a result.

Note that the print command can cause the ResizeFcn to be called if the PaperPositionMode property is set to manual and you have defined a resize function. If you do not want your resize function called by print, set the PaperPositionMode to auto.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

Selected

on | off (read only)

Is object selected? This property indicates whether the button group is selected. When this property is on, MATLAB displays selection handles if the SelectionHighlight property is also on. You can, for example, define the ButtonDownFcn function to set this property, allowing users to select the object with the mouse. SelectedObject scalar handle

Currently selected radio button or toggle button uicontrol in the managed group of components. Use this property to determine the currently selected component or to initialize selection of one of the radio buttons or toggle buttons. By default, SelectedObject is set to the first uicontrol radio button or toggle button that is added. Set it to [] if you want no selection. Note that SelectionChangeFcn does not execute when this property is set by the user.

SelectionChangeFcn

string or function handle

Callback routine executed when the selected radio button or toggle button changes. If this routine is called as a function handle, uibuttongroup passes it two arguments. The first argument, source, is the handle of the uibuttongroup. The second argument, eventdata, is an event data structure that contains the fields shown in the following table.

Event Data Structure Field	Description
EventName	'SelectionChanged'
OldValue	Handle of the object selected before this event. [] if none was selected.
NewValue	Handle of the currently selected object.

If you have a button group that contains a set of radio buttons and/or toggle buttons and you want an immediate action to occur when a radio button or toggle button is selected, you must include the code to control the radio and toggle buttons in the button group's SelectionChangeFcn callback function, not in the individual toggle button Callback functions. If you want another component such as a push button to base its action on the selection, then that component's Callback callback can get the handle of the selected radio button or toggle button from the button group's SelectedObject property.

Note For GUIDE GUIs, h0bject contains the handle of the selected radio button or toggle button. See "Examples: Programming GUIDE GUI Components" for more information.

SelectionHighlight

{on} | off

Object highlighted when selected. When the Selected property is on, MATLAB indicates the selected state by drawing four edge handles and four corner handles. When SelectionHighlight is off, MATLAB does not draw the handles.

ShadowColor

ColorSpec

3-D frame shadow color. ShadowColor is a three-element RGB vector or one of the MATLAB predefined names, specifying the shadow color. See the ColorSpec reference page for more information on specifying color.

Тад

string

User-specified object identifier. The Tag property provides a means to identify graphics objects with a user-specified label. You can define Tag as any string.

With the findobj function, you can locate an object with a given Tag property value. This saves you from defining object handles as global variables. For example, this function call returns the handles of all children (of the specified figures) that have the Tag value 'FormatTb'.

h = findobj(figurehandles, 'Tag', 'FormatTb')

Title

string

Title string. The text displayed in the button group title. You can position the title using the TitlePosition property.

If the string value is specified as a cell array of strings or padded string matrix, only the first string in the cell array or padded string matrix is displayed; the rest are ignored. Vertical slash ('|') characters are not interpreted as line breaks and instead show up in the text displayed in the uibuttongroup title.

Setting a property value to default, remove, or factory produces the effect described in "Defining Default Values". To set Title to one of these words, you must precede the word with the backslash character. For example,

```
hp = uibuttongroup(..., 'Title', '\Default');
```

TitlePosition

{lefttop} | centertop | righttop |
leftbottom | centerbottom | rightbottom

Location of the title. This property determines the location of the title string, in relation to the uibuttongroup.

Туре

string (read-only)

Object class. This property identifies the kind of graphics object. For uibuttongroup objects, Type is always the string 'uipanel', because its default properties derive from uipanels.

```
UIContextMenu
handle
```

Associate a context menu with a uibuttongroup. Assign this property the handle of a Uicontextmenu object. MATLAB displays the context menu whenever you right-click the uibuttongroup. Use the uicontextmenu function to create the context menu.

```
Units
```

inches | centimeters | {normalized} |
points | pixels | characters

Units of measurement. MATLAB uses these units to interpret the Position property. For the button group itself, units are measured from the lower-left corner of its parent figure window, panel, or button group. For children of the button group, they are measured from the lower-left corner of the button group.

- Normalized units map the lower-left corner of the button group or figure window to (0,0) and the upper-right corner to (1.0,1.0).
- pixels, inches, centimeters, and points are absolute units (1 point = 1/72 inch).
- Character units are characters using the default system font; the width of one character is the width of the letter x, the height of one character is the distance between the baselines of two lines of text.

If you change the value of Units, it is good practice to return it to its default value after completing your computation so as not to affect other functions that assume Units is set to the default value.

```
UserData
matrix
```

User-specified data. Any data you want to associate with the uibuttongroup object. MATLAB does not use this data, but you can access it using set and get.

Visible

{on} | off

Uibuttongroup visibility. By default, a uibuttongroup object is visible. When set to 'off', the uibuttongroup is not visible, as are all child objects of the button group. When a button group is hidden in this manner, you can still query and set its properties.


Note The value of a uibuttongroup's Visible property determines whether its child components, such as axes, buttons, uipanels, and other uibuttongroups, are visible. However, changing the Visible property of a button group does *not* change the settings of the Visible property of its child components even though hiding the button group causes them to be hidden.

uicontextmenu

Purpose	Create context menu
Syntax	handle = uicontextmenu(' <i>PropertyName</i> ',PropertyValue,)
Description	handle = uicontextmenu(' <i>PropertyName</i> ', PropertyValue,) creates a context menu, which is a menu that appears when the user right-clicks on a graphics object. See Uicontextmenu Properties for more information.
	In its initial state, a context menu has no menu items. You create menu items within the context menu using the uimenu function. Menu items appear in the order in which the uimenu statements appear. You then associate a context menu with an object by specifying the handle of the context menu as the value for its UIContextMenu property.
Example	<pre>The following statements define a context menu associated with a line on a graph. The menu items enable you to change the line style. % Create axes and save handle hax = axes; % Plot three lines plot(rand(20,3)); % Define a context menu; it is not attached to anything hcmenu = uicontextmenu; % Define callbacks for context menu items that change linestyle hcb1 = ['set(gco, ''LineStyle'', '''')']; hcb2 = ['set(gco, ''LineStyle'', ''-'')']; hcb3 = ['set(gco, ''LineStyle'', ''-'')']; % Define the context menu items and install their callbacks item1 = uimenu(hcmenu, 'Label', 'dashed', 'Callback', hcb1); item2 = uimenu(hcmenu, 'Label', 'solid', 'Callback', hcb2); item3 = uimenu(hcmenu, 'Label', 'solid', 'Callback', hcb3); % Locate line objects hlines = findall(hax, 'Type', 'line'); % Attach the context menu to each line for line = 1:length(hlines) set(hlines(line), 'uicontextmenu', hcmenu)</pre>

end

When you right-click on any line (or, on a Macintosh computer with a one-button mouse, press the **Ctrl** key and click), the context menu appears, as shown in the following figure.



To make context menus available immediately, attach them to lines at the time they are plotted. Therefore, when creating a GUI that uses such context menus, place code like the preceding in the callbacks that perform plotting for the GUI.

A best practice is to use function handles for callbacks. Only define callbacks as strings for simple actions. For example, you can add check marks to menu items (using the Checked uimenu property) to indicate the current style for each line. To manage the check marks, define the menu item callbacks as function handles. Place the code for the functions in the GUI code file rather than placing callback strings in the figure.

	Generally, you need to attach context menus to lines at the time they are plotted in order to be sure that the menus are immediately available. Therefore, code such as the above could be placed in or called from the callbacks that perform plotting for the GUI.
See Also	uibuttongroup, uicontrol, uimenu, uipanel
Tutorials	See "Context Menus" in the MATLAB Creating Graphical User Interfaces documentation.

Uicontextmenu Properties

Purpose	Describe context menu properties	
Modifying Properties	 You can set and query graphics object properties in two ways: The Property Inspector is an interactive tool that enables you to see and change object property values. The Property inspector is available from GUIDE, or use the inspect function at the command line. 	
	• The set and get functions enable you to set and query the values of properties.	
	For more information about changing the default value of a property see "Setting Default Property Values". For an example, see the CreateFcn property.	
Uicontext- menu Properties	This section lists all properties useful to uicontextmenu objects along with valid values and descriptions of their use. Curly braces {} enclose default values.	

Property	Purpose
BeingDeleted	This object is being deleted
BusyAction	Callback routine interruption
Callback	Control action
Children	The uimenus defined for the uicontextmenu
CreateFcn	Callback routine executed during object creation
DeleteFcn	Callback routine executed during object deletion
HandleVisibility	Whether handle is accessible from command line and GUIs
Interruptible	Callback routine interruption mode
Parent	Uicontextmenu object's parent

Property	Purpose
Position	Location of uicontextmenu when Visible is set to on
Тад	User-specified object identifier
Туре	Class of graphics object
UserData	User-specified data
Visible	Uicontextmenu visibility

BeingDeleted

on | {off} Read Only

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions might not need to perform actions on objects if the objects are going to be deleted, and therefore, can check the object's BeingDeleted property before acting.

BusyAction

cancel | {queue}

Callback routine interruption. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, the callback associated with the new event uses the value of BusyAction to decide whether or not to attempt to interrupt the executing callback.

• If the value is cancel, the event is discarded and the second callback does not execute.

• If the value is queue, and the Interruptible property of the first callback is on, the second callback is added to the event queue and executes in its turn after the first callback finishes execution.

Note If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. See the Interruptible property for information about controlling a callback's interruptibility.

Callback

string

Control action. A routine that executes whenever you right-click an object for which a context menu is defined. The routine executes immediately before the context menu is posted. Define this routine as a string that is a valid MATLAB expression or the name of a code file. The expression executes in the MATLAB workspace.

Children

matrix

The uimenu items defined for the uicontextmenu.

CreateFcn

string or function handle

Callback routine executed during object creation. The specified function executes when MATLAB creates a uicontextmenu object. MATLAB sets all property values for the uicontextmenu before executing the CreateFcn callback so these values are available to the callback. Within the function, use gcbo to get the handle of the uicontextmenu being created. Setting this property on an existing uicontextmenu object has no effect.

You can define a default CreateFcn callback for all new uicontextmenus. This default applies unless you override it by specifying a different CreateFcn callback when you call uicontextmenu. For example, the code

```
set(0,'DefaultUicontextmenuCreateFcn','set(gcbo,...
''Visible'',''on'')')
```

creates a default CreateFcn callback that runs whenever you create a new context menu. It sets the default Visible property of a context menu.

To override this default and create a context menu whose Visible property is set to a different value, call uicontextmenu with code similar to

```
hpt = uicontextmenu(...,'CreateFcn','set(gcbo,...
''Visible'',''off'')')
```

Note To override a default CreateFcn callback you must provide a new callback and not just provide different values for the specified properties. This is because the CreateFcn callback runs after the property values are set, and can override property values you have set explicitly in the uicontextmenu call. In the example above, if instead of redefining the CreateFcn property for this uicontextmenu, you had explicitly set Visible to off, the default CreateFcn callback would have set Visible back to the default, i.e., on.

Do not call copyobj or textwrap (which calls copyobj) inside a CreateFcn. The act of copying the uicontrol object fires the CreateFcn repeatedly, which raises a series of error messages after exceeding the root object's RecursionLimit property. See "Function Handle Callbacks" for information on how to use function handles to define a callback function.

DeleteFcn

string or function handle

Delete uicontextmenu callback routine. A callback routine that executes when you delete the uicontextmenu object (for example, when you issue a delete command or clear the figure containing the uicontextmenu). MATLAB executes the routine before destroying the object's properties so these values are available to the callback routine.

The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define a callback function.

HandleVisibility

{on} | callback | off

Control access to object's handle. This property determines when an object's handle is visible in its parent's list of children. When a handle is not visible in its parent's list of children, it is not returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close. Neither is the handle visible in the parent figure's CurrentObject property. Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

- Handles are always visible when HandleVisibility is on.
- Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from

the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.

• Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

You can set the root ShowHiddenHandles property to on to make all handles visible, regardless of their HandleVisibility settings. This does not affect the values of the HandleVisibility properties.

Interruptible

{on} | off

Callback routine interruption mode. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, that callback attempts to interrupt the first callback. MATLAB processes the callbacks according to these factors:

- The Interruptible property of the object whose callback is executing
- Whether the executing callback contains drawnow, figure, getframe, pause, or waitfor statements
- The BusyAction property of the object whose callback is waiting to execute

If the Interruptible property of the object whose callback is executing is on (the default), the callback can be interrupted. Whenever the callback calls one of the drawnow, figure, getframe, pause, or waitfor functions, the function processes any events in the event queue, including the waiting callback, before performing its defined task. If the Interruptible property of the object whose callback is executing is off, the callback cannot be interrupted (except by certain callbacks; see the note below). The BusyAction property of the object whose callback is waiting to execute determines what happens to the callback.

Note If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. The interrupting callback starts execution at the next drawnow, figure, getframe, pause, or waitfor statement. A figure's WindowButtonDownFcn callback routine, or an object's ButtonDownFcn or Callback routine are processed according to the rules described above.

Parent

handle

Uicontextmenu's parent. The handle of the uicontextmenu's parent object, which must be a figure.

Position

vector

Uicontextmenu's position. A two-element vector that defines the location of a context menu posted by setting the Visible property value to on. Specify Position as

[x y]

where vector elements represent the horizontal and vertical distances in pixels from the bottom left corner of the figure window, panel, or button group to the top left corner of the context menu.

Тад

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callback routines. You can define Tag as any string.

Туре

string

Class of graphics object. For uicontextmenu objects, Type is always the string 'uicontextmenu'.

UserData

matrix

User-specified data. Any data you want to associate with the uicontextmenu object. MATLAB does not use this data, but you can access it using set and get.

Visible

on | {off}

Uicontextmenu visibility. The Visible property can be used in two ways:

- Its value indicates whether the context menu is currently posted. While the context menu is posted, the property value is on; when the context menu is not posted, its value is off.
- Its value can be set to on to force the posting of the context menu. Similarly, setting the value to off forces the context menu to be removed. When used in this way, the Position property determines the location of the posted context menu.

See Also uicontextmenu

uicontrol

Purpose	Create user interface control object
Syntax	<pre>handle = uicontrol('PropertyName',PropertyValue,) handle = uicontrol(parent,'PropertyName',PropertyValue,) handle = uicontrol uicontrol(uich)</pre>
Description	uicontrol creates a uicontrol graphics objects (user interface controls), which you use to implement graphical user interfaces.
	handle = uicontrol(' <i>PropertyName</i> ', PropertyValue,) creates a uicontrol and assigns the specified properties and values to it. It assigns the default values to any properties you do not specify. The default uicontrol style is a pushbutton. The default parent is the current figure. See the Uicontrol Properties reference page for more information.
	handle = uicontrol(parent, ' <i>PropertyName</i> ', PropertyValue,) creates a uicontrol in the object specified by the handle, parent. If you also specify a different value for the Parent property, the value of the Parent property takes precedence. parent can be the handle of a figure, uipanel, or uibuttongroup.
	handle = uicontrol creates a pushbutton in the current figure. The uicontrol function assigns all properties their default values.
	uicontrol(uich) gives focus to the uicontrol specified by the handle, uich.
	When selected, most uicontrol objects perform a predefined action. MATLAB software supports numerous styles of uicontrols, each suited for a different purpose:
	• Check boxes
	• Editable text fields
	• Frames
	• List boxes

- Pop-up menus
- Push buttons
- Radio buttons
- Sliders
- Static text labels
- Toggle buttons

For information on using these uicontrols within GUIDE, the MATLAB GUI development environment, see Examples: Programming GUI Components in the MATLAB Creating GUIs documentation

Specifying the Uicontrol Style

To create a specific type of uicontrol, set the Style property as one of the following strings:

- 'checkbox' Check boxes generate an action when selected. These devices are useful when providing the user with a number of independent choices. To activate a check box, click the mouse button on the object. The state of the device is indicated on the display.
- 'edit' Editable text fields enable users to enter or modify text values. Use editable text when you want text as input. If Max-Min>1, then multiple lines are allowed. For multi-line edit boxes, a vertical scrollbar enables scrolling, as do the arrow keys.
- 'frame' Frames are rectangles that provide a visual enclosure for regions of a figure window. Frames can make a user interface easier to understand by grouping related controls. Frames have no callback routines associated with them. Only other uicontrols can appear within frames.

Frames are opaque, not transparent, so the order in which you define uicontrols is important in determining whether uicontrols within a frame are covered by the frame or are visible. *Stacking order* determines the order objects are drawn: objects defined first are drawn first; objects defined later are drawn over existing objects. If you use a frame to enclose objects, you must define the frame before you define the objects.

Note Most frames in existing GUIs can now be replaced with panels (uipanel) or button groups (uibuttongroup). GUIDE continues to support frames in those GUIs that contain them, but the frame component does not appear in the GUIDE Layout Editor component palette.

• 'listbox' - List boxes display a list of items and enable users to select one or more items. The Min and Max properties control the selection mode:

If Max-Min>1, then multiple selection is allowed.

If Max-Min<=1, then only single selection is allowed.

The Value property indicates selected entries and contains the indices into the list of strings; a vector value indicates multiple selections. MATLAB evaluates the list box's callback routine after any mouse button up event that changes the Value property. Therefore, you may need to add a "Done" button to delay action caused by multiple clicks on list items.

List boxes whose Enable property is on differentiate between single and double left clicks and set the figure SelectionType property to normal or open accordingly before evaluating the list box's Callback property. For such list boxes, Ctrl-left click and Shift-left click also set the figure SelectionType property to normal or open to indicate a single or double click.

 'popupmenu' – Pop-up menus (also known as drop-down menus or combo boxes) open to display a list of choices when pressed. When not open, a pop-up menu indicates the current choice. Pop-up menus are useful when you want to provide users with a number of mutually exclusive choices, but do not want to take up the amount of space that a series of radio buttons requires.

- 'pushbutton' Push buttons generate an action when pressed. To activate a push button, click the mouse button on the push button.
- 'radiobutton' Radio buttons are similar to check boxes, but are intended to be mutually exclusive within a group of related radio buttons (i.e., only one is in a pressed state at any given time). To activate a radio button, click the mouse button on the object. The state of the device is indicated on the display. Note that your code can implement mutually exclusive behavior for radio buttons.
- 'slider' Sliders accept numeric input within a specific range by enabling the user to move a sliding bar. Users move the bar by pressing the mouse button and dragging the pointer over the bar, or by clicking in the trough or on an arrow. The location of the bar indicates a numeric value, which is selected by releasing the mouse button. You can set the minimum, maximum, and current values of the slider.
- 'text' Static text boxes display lines of text. Static text is typically used to label other controls, provide directions to the user, or indicate values associated with a slider. Users cannot change static text interactively and there is no way to invoke the callback routine associated with it.
- 'togglebutton' Toggle buttons are controls that execute callbacks when clicked on and indicate their state, either on or off. Toggle buttons are useful for building toolbars.

Remarks

- Adding a uicontrol to a figure removes the figure toolbar when the figure's Toolbar property is set to 'auto' (which is the default). To prevent this from happening, set the Toolbar property to 'figure'. The user can restore the toolbar by selecting **Figure Toolbar** from the **View** menu regardless of this property setting.
 - The uicontrol function accepts property name/property value pairs, structures, and cell arrays as input arguments and optionally returns the handle of the created object. You can also set and query property values after creating the object using the set and get functions.

- A uicontrol object is a child of a figure, uipanel, or uibuttongroup and therefore does not require an axes to exist when placed in a figure window, uipanel, or uibuttongroup.
- When MATLAB is paused and a uicontrol has focus, pressing a keyboard key does not cause MATLAB to resume. Click anywhere outside a uicontrol and then press any key. See the pause function for more information.

Examples Example 1

The following statement creates a push button that clears the current axes when pressed.

```
h = uicontrol('Style', 'pushbutton', 'String', 'Clear',...
'Position', [20 150 100 70], 'Callback', 'cla');
```

This statement gives focus to the pushbutton.

uicontrol(h)

Example 2

You can create a uicontrol object that changes figure colormaps by specifying a pop-up menu and supplying an M-file name as the object's Callback:

```
hpop = uicontrol('Style', 'popup',...
'String', 'hsv|hot|cool|gray',...
'Position', [20 320 100 50],...
'Callback', 'setmap');
```

The above call to uicontrol defines four individual choices in the menu: hsv, hot, cool, and gray. You specify these choices with the String property, separating the choices with the "|" character.

The Callback, in this case setmap, is the name of an M-file that defines a more complicated set of instructions than a single MATLAB command. setmap contains these statements:

```
val = get(hpop, 'Value');
```

```
if val == 1
    colormap(hsv)
elseif val == 2
    colormap(hot)
elseif val == 3
    colormap(cool)
elseif val == 4
    colormap(gray)
end
```

The Value property contains a number that indicates the selected choice. The choices are numbered sequentially from one to four. The setmap M-file can get and then test the contents of the Value property to determine what action to take.

See Also textwrap, uibuttongroup, uimenu, uipanel

Uicontrol Properties

Purpose	Describe user interface control (uicontrol) properties			
Modifying Properties	 You can set and query graphics object properties in two ways: The Property Inspector is an interactive tool that enables you to see and change object property values. The Property inspector is available from GUIDE, or use the inspect function at the command line. The set and get commands enable you to set and query the values of properties To change the default value of properties see "Setting Default Property Values". You can also set default uicontrol properties on the root and figure levels: set(0, 'DefaultUicontrolProperty', PropertyValue) set(gcf, 'DefaultUicontrolProperty', PropertyValue) 			
	where <i>Property</i> is the name of the uicontrol property whose default value you want to set and <i>PropertyValue</i> is the value you are specifying as the default. Use set and get to access uicontrol properties.			
	For information on using these uicontrols within GUIDE, the MATLAB GUI development environment, see Programming GUI Components in the MATLAB Creating GUIs documentation.			
Uicontrol Properties	This section lists all properties useful to uicontrol objects along with valid values and descriptions of their use. Curly braces {} enclose default values.			
	Property	Purpose		
	BackgroundColor	Object background color		
	BeingDeleted	This object is being deleted		

Callback routine interruption

Button-press callback routine

BusyAction

ButtonDownFcn

Property	Purpose		
Callback	Control action		
CData	Truecolor image displayed on the control		
Children	Uicontrol objects have no children		
CreateFcn	Callback routine executed during object creation		
DeleteFcn	Callback routine executed during object deletion		
Enable	Enable or disable the uicontrol		
Extent	position rectangle (read only)		
FontAngle	Character slant		
FontName	Font family		
FontSize	Font size		
FontUnits	Font size units		
FontWeight	Weight of text characters		
ForegroundColor	Color of text		
HandleVisibility	Whether handle is accessible from command line and GUIs		
HitTest	Whether selectable by mouse click		
HorizontalAlignment	Alignment of label string		
Interruptible	Callback routine interruption mode		
KeyPressFcn	Key press callback routine		
ListboxTop	Index of top-most string displayed in list box		
Max	Maximum value (depends on uicontrol object)		
Min	Minimum value (depends on uicontrol object)		

Property	Purpose
Parent	Uicontrol object's parent
Position	Size and location of uicontrol object
Selected	Whether object is selected
SelectionHighlight	Object highlighted when selected
SliderStep	Slider step size
String	Uicontrol object label, also list box and pop-up menu items
Style	Type of uicontrol object
Tag	User-specified object identifier
TooltipString	Content of object's tooltip
Туре	Class of graphics object
UIContextMenu	Uicontextmenu object associated with the uicontrol
Units	Units to interpret position vector
UserData	User-specified data
Value	Current value of uicontrol object
Visible	Uicontrol visibility

BackgroundColor

ColorSpec

Object background color. The color used to fill the uicontrol rectangle. Specify a color using a three-element RGB vector or one of the MATLAB predefined names. The default color is determined by system settings. See ColorSpec for more information on specifying color.

```
BeingDeleted
```

on | {off} Read Only

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions might not need to perform actions on objects if the objects are going to be deleted, and therefore, can check the object's BeingDeleted property before acting.

BusyAction

cancel | {queue}

Callback routine interruption. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, the callback associated with the new event uses the value of BusyAction to decide whether or not to attempt to interrupt the executing callback.

- If the value is cancel, the event is discarded and the second callback does not execute.
- If the value is queue, and the Interruptible property of the first callback is on, the second callback is added to the event queue and executes in its turn after the first callback finishes execution.

Note If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. See the Interruptible property for information about controlling a callback's interruptiblity.

ButtonDownFcn

string or function handle (GUIDE sets this property)

Button-press callback routine. A callback routine that can execute when you press a mouse button while the pointer is on or near a uicontrol. Specifically:

- If the uicontrol's Enable property is set to on, the ButtonDownFcn callback executes when you click the right or left mouse button in a 5-pixel border around the uicontrol or when you click the right mouse button on the control itself.
- If the uicontrol's Enable property is set to inactive or off, the ButtonDownFcn executes when you click the right or left mouse button in the 5-pixel border or on the control itself.

This is useful for implementing actions to interactively modify control object properties, such as size and position, when they are clicked on (using selectmoveresize, for example).

Define this routine as a string that is a valid MATLAB expression or the name of a code file. The expression executes in the MATLAB workspace.

To add a ButtonDownFcn callback in GUIDE, select View Callbacks from the Layout Editor View menu, then select ButtonDownFcn. GUIDE sets this property to the appropriate string and adds the callback to the code file the next time you save the GUI. Alternatively, you can set this property to the string %automatic. The next time you save the GUI, GUIDE sets this property to the appropriate string and adds the callback to the code file.

Use the Callback property to specify the callback routine that executes when you activate the enabled uicontrol (e.g., click a push button).

Callback

string or function handle (GUIDE sets this property)

Control action. A routine that executes whenever you activate the uicontrol object (e.g., when you click on a push button or move a slider). Define this routine as a string that is a valid MATLAB expression or the name of a code file. The expression executes in the MATLAB workspace.

For examples of Callback callbacks for each style of component:

- For GUIDE GUIs, see "Examples: Programming GUIDE GUI Components".
- For programmatically created GUIs, see "Examples: Programming GUI Components".

Callback routines defined for static text do not execute because no action is associated with these objects.

To execute the callback routine for an edit text control, type in the desired text and then do one of the following:

- Click another component, the menu bar, or the background of the GUI.
- For a single line editable text box, press Enter.
- For a multiline editable text box, press Ctl+Enter.

CData

matrix

Truecolor image displayed on control. A three-dimensional matrix of RGB values that defines a truecolor image displayed on a control, which must be a **push button** or **toggle button**. Each value must be between 0.0 and 1.0. Setting CData on a **radio button** or **checkbox** will replace the default CData on these controls. The control will continue to work as expected, but its state is not reflected by its appearance when clicked. For **push buttons** and **toggle buttons**, **CData** overlaps the String. In the case of **radio buttons** and **checkboxes**, **CData** takes precedence over String and, depending on its size, it can displace the text.

Setting CData to [] restores the default CData for radio buttons and checkboxes.

Children

matrix

The empty matrix; uicontrol objects have no children.

Clipping

{on} | off

This property has no effect on uicontrol objects.

CreateFcn

string or function handle

Callback routine executed during object creation. The specified function executes when MATLAB creates a uicontrol object. MATLAB sets all property values for the uicontrol before executing the CreateFcn callback so these values are available to the callback. Within the function, use gcbo to get the handle of the uicontrol being created.

Setting this property on an existing uicontrol object has no effect.

You can define a default CreateFcn callback for all new uicontrols. This default applies unless you override it by specifying a different CreateFcn callback when you call uicontrol. For example, the code

```
set(0,'DefaultUicontrolCreateFcn','set(gcbo,...
''BackgroundColor'',''white'')')
```

creates a default CreateFcn callback that runs whenever you create a new uicontrol. It sets the default background color of all new uicontrols.

To override this default and create a uicontrol whose BackgroundColor is set to a different value, call uicontrol with code similar to

```
hpt = uicontrol(..., 'CreateFcn', 'set(gcbo,...
''BackgroundColor'', ''blue'')')
```

Note To override a default CreateFcn callback you must provide a new callback and not just provide different values for the specified properties. This is because the CreateFcn callback runs after the property values are set, and can override property values you have set explicitly in the uicontrol call. In the example above, if instead of redefining the CreateFcn property for this uicontrol, you had explicitly set BackgroundColor to blue, the default CreateFcn callback would have set BackgroundColor back to the default, i.e., white.

Do not call copyobj or textwrap (which calls copyobj) inside a CreateFcn. The act of copying the uicontrol object fires the CreateFcn repeatedly, which raises a series of error messages after exceeding the root object's RecursionLimit property.

See "Function Handle Callbacks" for information on how to use function handles to define a callback function.

DeleteFcn

string or function handle

Delete uicontrol callback routine. A callback routine that executes when you delete the uicontrol object (e.g., when you issue a delete command or clear the figure containing the uicontrol). MATLAB executes the routine before destroying the object's properties so these values are available to the callback routine.

The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define a callback function.

Enable

{on} | inactive | off

Enable or disable the uicontrol. This property controls how uicontrols respond to mouse button clicks, including which callback routines execute.

- on The uicontrol is operational (the default).
- inactive The uicontrol is not operational, but looks the same as when Enable is on.
- off The uicontrol is not operational and its image (set by the Cdata property) is grayed out.

When you left-click on a uicontrol whose Enable property is on, MATLAB performs these actions in this order:

- 1 Sets the figure SelectionType property.
- **2** Executes the uicontrol Callback routine, if any. (Static text components do not use callbacks.)
- **3** Does *not* set the figure CurrentPoint property and does *not* execute either the uicontrol ButtonDownFcn or the figure WindowButtonDownFcn callback.

Single-clicking or double-clicking an enabled uicontrol with the left mouse button sets the figure SelectionType property to normal, unless the uicontrol Style is listbox. For list boxes,

double-clicking sets the figure SelectionType property to open on the second of the two clicks, enabling the list box callback to detect a set of multiple choices.

When you left-click on a uicontrol whose Enable property is off or inactive, or when you right-click a uicontrol whose Enable property has any value, MATLAB performs these actions in this order:

- 1 Sets the figure SelectionType property.
- 2 Sets the figure CurrentPoint property.
- 3 Executes the figure WindowButtonDownFcn callback, if provided.
- 4 Executes the uicontrol ButtonDownFcn callback, if provided.

Extent

position rectangle (read only)

Size of uicontrol character string. A four-element vector that defines the size and position of the character string used to label the uicontrol. It has the form:

[0,0,width,height]

The first two elements are always zero. width and height are the dimensions of the rectangle. All measurements are in units specified by the Units property.

Since the Extent property is defined in the same units as the uicontrol itself, you can use this property to determine proper sizing for the uicontrol with regard to its label. Do this by

- Defining the String property and selecting the font using the relevant properties.
- Getting the value of the Extent property.
- Defining the width and height of the Position property to be somewhat larger than the width and height of the Extent.

For multiline strings, the Extent rectangle encompasses all the lines of text. For single line strings, the height element of the Extent property returned always indicates the height of a single line, and its width element always indicates the width of the longest line, even if the string wraps when displayed on the control. Edit boxes are considered multiline if Max - Min > 1.

FontAngle

{normal} | italic | oblique

Character slant. MATLAB uses this property to select a font from those available on your particular system. Setting this property to italic or oblique selects a slanted version of the font, when it is available on your system.

FontName

string

Font family. The name of the font in which to display the String. To display and print properly, this must be a font that your system supports. The default font is system dependent.

Note MATLAB GUIs do not support the Marlett and Symbol font families.

To use a fixed-width font that looks good in any locale (and displays properly in Japan, where multibyte character sets are used), set FontName to the string FixedWidth (this string value is case sensitive):

```
set(uicontrol handle, 'FontName', 'FixedWidth')
```

This parameter value eliminates the need to hard code the name of a fixed-width font, which may not display text properly on systems that do not use ASCII character encoding (such as in Japan). A properly written MATLAB application that needs to use a fixed-width font should set FontName to FixedWidth and rely on the root FixedWidthFontName property to be set correctly in the end user's environment.

End users can adapt a MATLAB application to different locales or personal environments by setting the root FixedWidthFontName property to the appropriate value for that locale from startup.m. Setting the root FixedWidthFontName property causes an immediate update of the display to use the new font.

Tip To determine what fonts exist on your system (which can differ from the GUI user's system), use the uisetfont GUI to select a font and return its name and other characteristics in a MATLAB structure.

FontSize

size in FontUnits

Font size. A number specifying the size of the font in which to display the String, in units determined by the FontUnits property. The default point size is system dependent.

FontUnits

{points} | normalized | inches |
centimeters | pixels

Font size units. This property determines the units used by the FontSize property. Normalized units interpret FontSize as a fraction of the height of the uicontrol. When you resize the uicontrol, MATLAB modifies the screen FontSize accordingly. pixels, inches, centimeters, and points are absolute units (1 point = $\frac{1}{72}$ inch).

FontWeight

light | {normal} | demi | bold

Weight of text characters. MATLAB uses this property to select a font from those available on your particular system. Setting this property to **bold** causes MATLAB to use a bold version of the font, when it is available on your system.

ForegroundColor ColorSpec

Color of text. This property determines the color of the text defined for the String property (the uicontrol label). Specify a color using a three-element RGB vector or one of the MATLAB predefined names. The default text color is black. See ColorSpec for more information on specifying color.

HandleVisibility

{on} | callback | off

Control access to object's handle. This property determines when an object's handle is visible in its parent's list of children. When a handle is not visible in its parent's list of children, it is not returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close. Neither is the handle visible in the parent figure's CurrentObject property. Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

- Handles are always visible when HandleVisibility is on.
- Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.
- Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine

invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

You can set the root ShowHiddenHandles property to on to make all handles visible, regardless of their HandleVisibility settings. This does not affect the values of the HandleVisibility properties.

Note Radio buttons and toggle buttons that are managed by a uibuttongroup should not be accessed outside the button group. Set the HandleVisibility of such radio buttons and toggle buttons to off to prevent inadvertent access.

HitTest

{on} | off

Selectable by mouse click. This property has no effect on uicontrol objects.

HorizontalAlignment

left | {center} | right

Horizontal alignment of label string. This property determines the justification of the text defined for the String property (the uicontrol label):

- left Text is left justified with respect to the uicontrol.
- center Text is centered with respect to the uicontrol.
- right Text is right justified with respect to the uicontrol.

On Microsoft Windows systems, this property affects only edit and text uicontrols.

Interruptible
 {on} | off

Callback routine interruption mode. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, that callback attempts to interrupt the first callback. MATLAB processes the callbacks according to these factors:

- The Interruptible property of the object whose callback is executing
- Whether the executing callback contains drawnow, figure, getframe, pause, or waitfor statements
- The BusyAction property of the object whose callback is waiting to execute

If the Interruptible property of the object whose callback is executing is on (the default), the callback can be interrupted. Whenever the callback calls one of the drawnow, figure, getframe, pause, or waitfor functions, the function processes any events in the event queue, including the waiting callback, before performing its defined task.

If the Interruptible property of the object whose callback is executing is off, the callback cannot be interrupted (except by certain callbacks; see the note below). The BusyAction property of the object whose callback is waiting to execute determines what happens to the callback. **Note** If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. The interrupting callback starts execution at the next drawnow, figure, getframe, pause, or waitfor statement. A figure's WindowButtonDownFcn callback routine, or an object's ButtonDownFcn or Callback routine are processed according to the rules described above.

KeyPressFcn

string or function handle

Key press callback function. A callback routine invoked by a key press when the callback's uicontrol object has focus. Focus is denoted by a border or a dotted border, respectively, in UNIX and Microsoft Windows. If no uicontrol has focus, the figure's key press callback function, if any, is invoked. KeyPressFcn can be a function handle, the name of a code file, or any legal MATLAB expression.

If the specified value is the name of a code file, the callback routine can query the figure's CurrentCharacter property to determine what particular key was pressed and thereby limit the callback execution to specific keys.

If the specified value is a function handle, the callback routine can retrieve information about the key that was pressed from its event data structure argument.

Event Data			Examples:			
Structure Field	Description	a	=	Shift	Shift/a	
Character	Character interpretation of the key that was pressed.	'a'	'='	11	'A'	
Modifier	Current modifier, such as 'control', or an empty cell array if there is no modifier	{1x0 cell}	{1x0 cell}	{'shift'	'}{'shift'}	
Кеу	Name of the key that was pressed.	'a'	'equal'	'shift'	'a'	

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

ListboxTop

scalar

Index of top-most string displayed in list box. This property applies only to the listbox style of uicontrol. It specifies which string appears in the top-most position in a list box that is not large enough to display all list entries. ListboxTop is an index into the array of strings defined by the String property and must have a value between 1 and the number of strings. Noninteger values are fixed to the next lowest integer.

Max

scalar

Maximum value. This property specifies the largest value allowed for the Value property. Different styles of uicontrols interpret Max differently:

- Check boxes Max is the setting of the Value property while the check box is selected.
- Editable text The Value property does not apply. If Max Min
 > 1, then editable text boxes accept multiline input. If Max Min

<= 1, then editable text boxes accept only single line input. The absolute values of Max and Min have no effect on the number of lines an edit box can contain; a multiline edit box can contain any number of lines.

- List boxes If Max Min > 1, then list boxes allow multiple item selection. If Max Min <= 1, then list boxes do not allow multiple item selection. When they do, Value can be a vector of indices.
- Radio buttons Max is the setting of the Value property when the radio button is selected.
- Sliders Max is the maximum slider value and must be greater than the Min property. The default is 1.
- Toggle buttons Max is the value of the Value property when the toggle button is selected. The default is 1.
- Pop-up menus, push buttons, and static text do not use the Max property.

Min

scalar

Minimum value. This property specifies the smallest value allowed for the Value property. Different styles of uicontrols interpret Min differently:

- Check boxes Min is the setting of the Value property while the check box is not selected.
- Editable text The Value property does not apply. If Max Min > 1, then editable text boxes accept multiline input. If Max Min <= 1, then editable text boxes accept only single line input. The absolute values of Max and Min have no effect on the number of lines an edit box can contain; a multiline edit box can contain any number of lines.
- List boxes If Max Min > 1, then list boxes allow multiple item selection. If Max Min <= 1, then list boxes allow only single item selection. When they do, Value can be a vector of indices.

- Radio buttons Min is the setting of the Value property when the radio button is not selected.
- Sliders Min is the minimum slider value and must be less than Max. The default is 0.
- Toggle buttons Min is the value of the Value property when the toggle button is not selected. The default is 0.
- Pop-up menus, push buttons, and static text do not use the Min property.

Parent

handle

Uicontrol parent. The handle of the uicontrol's parent object. You can move a uicontrol object to another figure, uipanel, or uibuttongroup by setting this property to the handle of the new parent.

Position

position rectangle

Size and location of uicontrol. The rectangle defined by this property specifies the size and location of the control within the parent figure window, uipanel, or uibuttongroup. Specify **Position** as

[left bottom width height]

left and bottom are the distance from the lower-left corner of the parent object to the lower-left corner of the uicontrol object. width and height are the dimensions of the uicontrol rectangle. All measurements are in units specified by the Units property.

On Microsoft Windows systems, the height of pop-up menus is automatically determined by the size of the font. The value you specify for the height of the Position property has no effect. The width and height values determine the orientation of sliders. If width is greater than height, then the slider is oriented horizontally, If height is greater than width, then the slider is oriented vertically.

Note The height of a pop-up menu is determined by the font size. The height you set in the position vector is ignored. The height element of the position vector is not changed.

On Mac platforms, the height of a horizontal slider is constrained. If the height you set in the position vector exceeds this constraint, the displayed height of the slider is the maximum allowed. The height element of the position vector is not changed.

Selected

on | {off} (read only)

Is object selected. When this property is on, MATLAB displays selection handles if the SelectionHighlight property is also on. You can, for example, define the ButtonDownFcn to set this property, allowing users to select the object with the mouse.

SelectionHighlight

{on} | off

Object highlight when selected. When the Selected property is on, MATLAB indicates the selected state by drawing four edge handles and four corner handles. When SelectionHighlight is off, MATLAB does not draw the handles.

SliderStep

[min_step max_step]

Slider step size. This property controls the amount the slider Value changes when you click the mouse on the arrow button (min_step) or on the slider trough (max_step). Specify

SliderStep as a two-element vector; each value must be in the range [0,1], and min_step should be less than max_step. Numbers outside [0 1] can cause the slider not to render or produce unexpected results. The actual step size is a function of the specified SliderStep and the total slider range (Max - Min). The default, [0.01 0.10], provides a 1 percent change for clicks on the arrow button and a 10 percent change for clicks in the trough. and both should be positive numbers less then 1.

For example, if you create the following slider,

uicontrol('Style','slider','Min',1,'Max',7,... 'Value',2,'SliderStep',[0.1 0.6])

clicking on the arrow button moves the indicator by,

0.1*(7-1) ans = 0.6000

and clicking in the trough moves the indicator by,

```
0.6*(7-1)
ans =
3.6000
```

Note that if the specified step size moves the slider to a value outside the range, the indicator moves only to the Max or Min value.

See also the Max, Min, and Value properties.

String

string

Uicontrol label, list box items, pop-up menu choices.

For check boxes, editable text, push buttons, radio buttons, static text, and toggle buttons, the text displayed on the object.

For list boxes and pop-up menus, the set of entries or items displayed in the object.

Note If you specify a numerical value for String, MATLAB converts it to char but the result may not be what you expect. If you have numerical data, you should first convert it to a string, e.g., using num2str, before assigning it to the String property.

For uicontrol objects that display only one line of text (check box, push button, radio button, toggle button), if the string value is specified as a cell array of strings or padded string matrix, only the first string of a cell array or of a padded string matrix is displayed; the rest are ignored. Vertical slash ('|') characters are not interpreted as line breaks and instead show up in the text displayed in the uicontrol.

For multiple line editable text or static text controls, line breaks occur between each row of the string matrix, and each cell of a cell array of strings. Vertical slash ('|') characters and \n characters are not interpreted as line breaks, and instead show up in the text displayed in the uicontrol.

For multiple items on a list box or pop-up menu, you can specify the items in any of the formats shown in the following table.

String Property Format	Example
Cell array of strings	{'one' 'two' 'three'}
Padded string matrix	['one ';'two ';'three']
String vector separated by vertical slash () characters	['one two three']

If you specify a component width that is too small to accommodate one or more of the specified strings, MATLAB truncates those strings with an ellipsis. Use the Value property to set the index of the initial item selected.

For check boxes, push buttons, radio buttons, toggle buttons, and the selected item in **popup menus**, when the specified text is clipped because it is too long for the uicontrol, an ellipsis (...) is appended to the text in the active GUI to indicate that it has been clipped.

For **push buttons** and **toggle buttons**, **CData** overlaps the String. In the case of **radio buttons** and **checkboxes**, **CData** takes precedence over String and, depending on its size, can displace the text.

For **editable text**, the String property value is set to the string entered by the user.

Reserved Words There are three reserved words: default, remove, factory (case sensitive). If you want to use one of these reserved words in the String property, you must precede it with a backslash ('\') character. For example,

```
h = uicontrol('Style','edit','String','\default');
```

Style

{pushbutton} | togglebutton | radiobutton | checkbox |
edit | text | slider | frame | listbox | popupmenu

Style of uicontrol object to create. The Style property specifies the kind of uicontrol to create. See the uicontrol Description section for information on each type.

Тад

string (GUIDE sets this property)

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callback routines. You can define Tag as any string.

TooltipString

string

Content of tooltip for object. The TooltipString property specifies the text of the tooltip associated with the uicontrol. When the user moves the mouse pointer over the control and leaves it there, the tooltip is displayed.

To create a tooltip that has more than one line of text, use sprintf to generate a string containing newline (\n) characters and then set the TooltipString to that value. For example:

```
h = uicontrol('Style','pushbutton');
s = sprintf('Button tooltip line 1\nButton tooltip line 2');
set(h,'TooltipString',s)
```

Туре

string (read only)

Class of graphics object. For uicontrol objects, Type is always the string 'uicontrol'.

UIContextMenu

handle

Associate a context menu with uicontrol. Assign this property the handle of a uicontextmenu object. MATLAB displays the context menu whenever you right-click over the uicontrol. Use the uicontextmenu function to create the context menu.

Units

{pixels} | normalized | inches | centimeters | points |
characters (GUIDE default: normalized)

Units of measurement. MATLAB uses these units to interpret the Extent and Position properties. All units are measured from the lower-left corner of the parent object.

- Normalized units map the lower-left corner of the parent object to (0,0) and the upper-right corner to (1.0,1.0).
- pixels, inches, centimeters, and points are absolute units (1 point = 1/72 inch).
- Character units are characters using the default system font; the width of one character is the width of the letter x, the height of one character is the distance between the baselines of two lines of text.

If you change the value of Units, it is good practice to return it to its default value after completing your computation so as not to affect other functions that assume Units is set to the default value.

UserData

matrix

User-specified data. Any data you want to associate with the uicontrol object. MATLAB does not use this data, but you can access it using set and get.

Value

scalar or vector

Current value of uicontrol. The uicontrol style determines the possible values this property can have:

- Check boxes set Value to Max when they are on (when selected) and Min when off (not selected).
- List boxes set Value to a vector of indices corresponding to the selected list entries, where 1 corresponds to the first item in the list.
- Pop-up menus set Value to the index of the item selected, where 1 corresponds to the first item in the menu. The Examples section shows how to use the Value property to determine which item has been selected.
- Radio buttons set Value to Max when they are on (when selected) and Min when off (not selected).
- Sliders set Value to the number indicated by the slider bar.
- Toggle buttons set Value to Max when they are down (selected) and Min when up (not selected).
- Editable text, push buttons, and static text do not set this property.

Set the Value property either interactively with the mouse or through a call to the set function. The display reflects changes made to Value.

```
Visible
```

{on} | off

Uicontrol visibility. By default, all uicontrols are visible. When set to off, the uicontrol is not visible, but still exists and you can query and set its properties.

Note Setting Visible to off for uicontrols that are not displayed initially in the GUI, can result in faster startup time for the GUI.

Purpose	Open standard dialog box for selecting directory				
Syntax	folder_name = uigetdir folder_name = uigetdir(start_path) folder_name = uigetdir(start_path,dialog_title)				
Description	<pre>folder_name = uigetdir displays a modal dialog box enabling the user to navigate the folder hierarchy and select a folder or type the name of a folder. If the folder exists, uigetdir returns the selected path when the user clicks OK. If the user types the name of a folder that does not exist, uigetdir returns the name of the current folder. If the user clicks Cancel or closes the dialog window, uigetdir returns 0. On Microsoft Windows platforms, uigetdir opens a dialog box in the base folder (the Windows desktop) with the current folder selected.</pre>				
	<pre>folder_name = uigetdir(start_path) opens a dialog box with the folder specified by start_path selected. If start_path is a valid path, the dialog box opens in the specified folder. If start_path is an empty string ('') or is not a valid path, the dialog box opens in the current folder.</pre>				
	<pre>folder_name = uigetdir(start_path,dialog_title) opens a dialog box with the specified title. On Windows and UNIX platforms, the string replaces the default caption inside the dialog box for specifying instructions to the user. The default dialog_title is Select folder to Open.</pre>				
	On Windows platforms, you can click the New Folder button to add a new folder to the folder hierarchy displayed. You can also drag and drop existing directories into different folders.				
	On UNIX platforms, uigetdir opens a dialog box in the startup folder (the one you are in when you start MATLAB), with the current directory selected. The dialog_title string replaces the default title of the dialog box. The dialog box looks like the one shown in the following figure.				

		Select D	irectory	to Oper	n				×
Look <u>i</u> n: 🗀 M	1ATLABFiles			•			*		1
custhelp databaseto matlab_file: mymfiles published quick_ref_tr	s								
File <u>N</u> ame:	/home/MAT	FLABFiles							
Files of <u>T</u> ype:	All Files								-
				[ок		Cancel	

On Mac platforms, uigetdir opens a dialog box in the startup folder (the one you are in when you start MATLAB), with the current directory selected. The dialog box is like the one shown in the following figure.

Name	▲ Date Modified
📁 Folder 2	Today, 4:59 PM
Folder 11	Today, 4:59 PM
Folder 12	Today, 4:59 PM
Folder 14	Today, 4:59 PM
Folder 3	Today, 4:59 PM
onek.ps	Wednesday, November 15, 2006, 4:52 PM
🗑 onek2.ps	Wednesday, November 15, 2006, 4:52 PM
onekc.ps	Wednesday, November 15, 2006, 4:52 PM
🕐 onekc2.ps	Wednesday, November 15, 2006, 4:52 PM
ps3file.ps	Wednesday, November 15, 2006, 4:37 PM
psc2file.ps	Wednesday, November 15, 2006, 4:38 PM
pscfile.ps	Wednesday, November 15, 2006, 4:38 PM
👰 psfile.ps	Wednesday, November 15, 2006, 4:37 PM
📁 tp380702	Thursday, November 16, 2006, 9:42 AM


Note A modal dialog box prevents you from interacting with other MATLAB windows before responding. To block MATLAB program execution as well, use the uiwait function. For more information about modal dialog boxes, see WindowStyle in the MATLAB Figure Properties.

The pwd and cd functions return the name of the current folder.

Examples The following statement displays directories on the C: drive.

dname = uigetdir('C:\');

The dialog box displays as follows (on Windows).



Selecting the directory ${\tt Desktop},$ as shown in the figure, and clicking ${\sf OK},$ uigetdir returns

```
dname =
C:\WINNT\Profiles\All Users\Desktop
```

The following statement uses the matlabroot command to display the MATLAB root directory in the dialog box:

Browse For Folder	? ×
MATLAB Root Directory	
🚊 🛄 MATLAB6p5	_
😟 🕀 💼 bin	
demos	
😟 🕀 💼 extern	
😟 🕀 💼 help	
🔂 ja	_
😟 🕀 💼 java	
🖻 💭 notebook	
🗄 🛄 sys	
😟 庄 🛄 toolbox	
🗉 🗋 🛄 uninstall	-
OK Cancel	New Folder

uigetdir(matlabroot, 'MATLAB Root Directory')

Selecting the directory MATLAB6.5/notebook/pc, as shown in the figure, returns a string like % f(x) = 0

C:\MATLAB6.5\notebook\pc

assuming that MATLAB is installed on drive $\texttt{C:} \$

See Also uigetfile, uiputfile

Purpose	Open standard dialog box for retrieving files				
Syntax	<pre>filename = uigetfile [FileName,PathName,FilterIndex] = uigetfile(FilterSpec) [FileName,PathName,FilterIndex] = uigetfile(FilterSpec, DialogTitle) [FileName,PathName,FilterIndex] = uigetfile(FilterSpec, DialogTitle,DefaultName) [FileName,PathName,FilterIndex] = uigetfile(,'MultiSelect', selectmode)</pre>				

Description Description

filename = uigetfile displays a modal dialog box that lists files in the current folder and enables you to select or enter the name of a file. If the filename is valid and if the file exists, uigetfile returns the filename as a string when you click **Open**. Otherwise uigetfile displays an appropriate error message, after which control returns to the dialog box. You can then enter another filename or click **Cancel**. If you click **Cancel** or close the dialog window, uigetfile returns 0. Successful execution of uigetfile does not open a file; it only returns the name of an existing file that you identify.

[FileName,PathName,FilterIndex] = uigetfile(FilterSpec) displays only those files with extensions that match FilterSpec. On some platforms uigetfile also displays the files that do not match FilterSpec in grey. The uigetfile function appends 'All Files' to the list of file types. FilterSpec can be a string or a cell array of strings, and can include the * wildcard.

- If FilterSpec is a filename, that filename displays, selected in the **File name** field. The extension of the file is the default filter.
- FilterSpec can include a path. That path can contain '.','..', \, '/', or '~'. For example, '../*.m' lists all code files in the folder above the current folder.
- If FilterSpec is a folder name, uigetfile displays the contents of that folder, the **File name** field is empty, and no filter applies. To

specify a folder name, make the last character of FilterSpec either '\' or '/'.

• If FilterSpec is a cell array of strings, it can include two columns. The first column contains a list of file extensions. The optional second column contains a corresponding list of descriptions. These descriptions replace standard descriptions in the **Files of type** field. A description cannot be an empty string. The second and third examples illustrate use of a cell array as FilterSpec.

If FilterSpec is missing or empty, uigetfile uses the default list of file types (for example, all MATLAB files).

After you click **Open** and if the filename exists,**uigetfile** returns the name of the file in FileName and its path in PathName. If you click **Cancel** or close the dialog window, the function sets FileName and PathName to 0.

FilterIndex is the index of the filter selected in the dialog box. Indexing starts at 1. If you click **Cancel** or close the dialog window, the function sets FilterIndex to 0.

```
[FileName,PathName,FilterIndex] =
uigetfile(FilterSpec,DialogTitle) displays a dialog box that
has the title DialogTitle. To use the default file types and specify a
dialog title, enter
```

```
uigetfile('',DialogTitle)
```

```
[FileName,PathName,FilterIndex] =
```

uigetfile(FilterSpec,DialogTitle,DefaultName) displays a dialog box in which the filename specified by DefaultName appears in the File name field. DefaultName can also be a path or a path/filename. In this case, uigetfile opens the dialog box in the folder specified by the path. You can use '.','..', \, or '/' in the DefaultName argument. To specify a folder name, make the last character of DefaultName either '\' or '/'. If the specified path does not exist, uigetfile opens the dialog box in the current folder. [FileName,PathName,FilterIndex] =

uigetfile(..., 'MultiSelect', *selectmode*) opens the dialog in *multiselect* mode. Valid values for *selectmode* are 'on' and 'off' (the default, which allows single selection only). If 'MultiSelect' is 'on' and you select more than one file in the dialog box, then FileName is a cell array of strings. Each array element contains the name of a selected file. Filenames in the cell array are sorted in the order your platform uses. Because multiple selections are always in the same folder, PathName is always a string identifying a single folder.

If you include either of the "wildcard" characters '*' or '?' in a file name, uigetfile does not respond to clicking **Open**. The dialog box remains open until you cancel it or remove the wildcard characters. This restriction applies to all platforms, even to file systems that permit these characters in file names.

For Microsoft Windows platforms, the dialog box is the Windows dialog box native to your platform. Depending on your version of Windows, dialogs you see can differ from the figures shown in following examples.

For UNIX platforms, the dialog box is like the one shown in the following figure.

Select F	ile to Open 🛛 🗙
Look In: 🗀 MATLABFiles	- 🛍 🕍 📴 🖿
Custhelp help_locator. databasetoolboxfiles loopcountfile. matlab_files matlab.mat mymfiles myfcn.m published newprofile.m quick_ref_training newprofile.m collatznew.m oldprofile.m Contents.m oldprofile.help fileassoc.m outputtest.m	m 📄 rtw_solver_tp.m
File <u>N</u> ame: Files of <u>Type</u> : MATLAB files	Open Cancel

For Mac platforms, the dialog box is like the one shown in the following figure.

work	•
Name	Date Modified
🖹 dolphin.gif	Wednesday, November 15, 2006 5:03 PM
👻 onek.ps	Wednesday, November 15, 2006 4:52 PM
👻 onek2.ps	Wednesday, November 15, 2006 4:52 PM
👻 onekc.ps	Wednesday, November 15, 2006 4:52 PM
👻 onekc2.ps	Wednesday, November 15, 2006 4:52 PM
👻 ps3file.ps	Wednesday, November 15, 2006 4:37 PM
👻 psc2file.ps	Wednesday, November 15, 2006 4:38 PM
👻 pscfile.ps	Wednesday, November 15, 2006 4:38 PM
👻 psfile.ps	Wednesday, November 15, 2006 4:37 PM
📁 tp380702	Thursday, November 16, 2006 9:42 AM
UpdatePatch.txt	Wednesday, November 15, 2006 6:17 PM
UpdatePatch.txt~	Thursday, November 16, 2006 5:05 AM
verify_exported_files.m	Wednesday, November 15, 2006 4:35 PM
File Format:	All Files

Note A modal dialog box prevents you from interacting with other windows before responding. To block MATLAB program execution, use the uiwait function. For more information about modal dialog boxes, see WindowStyle in the MATLAB Figure Properties.

Examples

The following statement displays a dialog box for retrieving a file. The dialog lists all MATLAB code files within a selected directory. uigetfile returns the name and path of the selected file in FileName and PathName. uigetfile appends All Files(*.*) to the file types when FilterSpec is a string.

```
[FileName,PathName] = uigetfile('*.m','Select the MATLAB code file');
```

The following figure shows the dialog box.

Select the M-fil	2					<u>? ×</u>
Look in	🗁 Work		•	🗕 🖻	• 🎫 🕶	
Desktop Desktop My Documents My Computer My Network Places	button_callback colorPalette.m iconEditor.m iconRead.m slider_gui.m two_axes.m	m				
	File name:	*.m		•		Open
	Files of type:	M-files (*.m)		•		Cancel
		M-files (*.m) All Files (*.*)				

To create a list of file types that appears in the **Files of type** list box, separate the file extensions with semicolons, as in the following code. uigetfile displays a default description for each known file type, such as "Model files" for Simulink.mdl files.

```
[filename, pathname] = ...
uigetfile({'*.m';'*.mdl';'*.mat';'*.*'},'File Selector');
```


uigetfile

File Selector					<u>?×</u>
Look in:	🗀 Work		•	+ 🗈 💣 🗉	
Desktop Desktop My Documents My Computer My Network Places	button_callbad colorPalette.m iconEditor.m iconRead.m slider_gui.m two_axes.m	.m			
	File name:			•	Open
	Files of type:	M-files (*.m) M-files (*.m) Model files (*.mdl MAT-files (*.mat) All Files (*.*))		Cancel

If you want to create a list of file types and give them descriptions that are different from the defaults, use a cell array, as in the following code. This example also associates multiple file types with the 'MATLAB Files' description.

```
[filename, pathname] = uigetfile( ...
{'*.m;*.fig;*.mat;*.mdl','MATLAB Files (*.m,*.fig,*.mat,*.mdl)';
    '*.m', 'Code files (*.m)'; ...
    '*.fig','Figures (*.fig)'; ...
    '*.mat','MAT-files (*.mat)'; ...
    '*.mdl','Models (*.mdl)'; ...
    '*.*', 'All Files (*.*)'}, ...
'Pick a file');
```

The first column of the cell array contains the file extensions, while the second contains your descriptions of the file types. In this example, the first entry of column one contains several extensions, separated by semicolons, which are all associated with the description 'MATLAB Files (*.m,*.fig,*.mat,*.mdl)'. The code produces the dialog box shown in the following figure.



The following code lets you identify a file and then displays a message summarizing the result.

```
[filename, pathname] = uigetfile('*.m', 'Select a MATLAB code file');
if isequal(filename,0)
```

```
disp('User selected Cancel')
else
    disp(['User selected', fullfile(pathname, filename)])
end
```

Pick an M-file ? × Look in: 🛅 Work • 🖛 🗈 💣 🎟 button_callback.m 4 close button.m Desktop colorPalette.m conEditor.m iconRead.m simple_gui.m My Documents slider_gui.m two_axes.m J untitled 1.m My Computer My Network Places *.m • File name: Open Cancel Files of type: M-files (*.m) • M-files (*.m) All Files (*.*)


This example creates a list of file types and gives them descriptions that are different from the defaults. It also enables multiple file selection. You can select multiple files by holding down the **Shift** or **Ctrl** key and clicking on additional file names.

```
[filename, pathname, filterindex] = uigetfile( ...
{ '*.mat','MAT-files (*.mat)'; ...
'*.mdl','Models (*.mdl)'; ...
'*.*', 'All Files (*.*)'}, ...
'Pick a file', ...
```



As mentioned previously, **uigetfile** does not open the file or files you select.

This example uses the DefaultName argument to specify a start path and a default filename for the dialog box.



- **Alternatives** Use the dir function to return a filtered or unfiltered list of files in your current folder or a folder you specify. dir also can return file attributes.
- See Also uigetdir, uiopen, uiputfile

uigetpref

Purpose	Open dialog box for retrieving preferences					
Syntax	value = uigetpref(group,pref,title,question,pref_choices) [val,dlgshown] = uigetpref()					
Description	<pre>value = uigetpref(group,pref,title,question,pref_choices) returns one of the strings in pref_choices, by doing one of the following:</pre>					
	• Prompting the user with a multiple-choice question dialog box					
	• Returning a previous answer stored in the preferences database					
	By default, the dialog box is shown, with each choice on a different pushbutton, and with a checkbox controlling whether the returned value should be stored in preferences and automatically reused in subsequent invocations.					
	If the user checks the checkbox before choosing one of the push buttons, the push button choice is stored in preferences and returned in value. Subsequent calls to uigetpref detect that the last choice was stored in preferences, and return that choice immediately without displaying the dialog.					
	If the user does not check the checkbox before choosing a pushbutton, the selected preference is not stored in preferences. Rather, a special value, 'ask', is stored, indicating that subsequent calls to uigetpref should display the dialog box.					
Note uigetpref uses the same preference database as addpref getpref, ispref, rmpref, and setpref. However, it registers th preferences it sets in a separate list so that it, and uisetpref, cadistinguish those preferences that are being managed with uiget						
	For preferences registered with uigetpref, you can use setpref and uisetpref to explicitly change preference values to 'ask'.					

group and pref define the preference. If the preference does not already exist, uigetpref creates it.

title defines the string displayed in the dialog box titlebar.

question is a descriptive paragraph displayed in the dialog, specified as a string array or cell array of strings. This should contain the question the user is being asked, and should be detailed enough to give the user a clear understanding of their choice and its impact. uigetpref inserts line breaks between rows of the string array, between elements of the cell array of strings, or between '|' or newline characters in the string vector.

pref_choices is either a string, cell array of strings, or '|'-separated strings specifying the strings to be displayed on the push buttons. Each string element is displayed in a separate push button. The string on the selected pushbutton is returned.

Make pref_choices a 2-by-n cell array of strings if the internal preference values are different from the strings displayed on the pushbuttons. The first row contains the preference strings, and the second row contains the related pushbutton strings. Note that the preference values are returned in value, not the button labels.

[val,dlgshown] = uigetpref(...) returns whether or not the dialog was shown.

Additional arguments can be passed in as parameter-value pairs:

 $(\dots$ 'CheckboxState', state) sets the initial state of the checkbox, either checked or unchecked. state can be either 0 (unchecked) or 1 (checked). By default it is 0.

(...'CheckboxString',cbstr) sets the string cbstr on the checkbox. By default it is 'Never show this dialog again'.

(... 'HelpString', hstr) sets the string hstr on the help button. By default the string is empty and there is no help button.

(... 'HelpFcn', hfcn) sets the callback that is executed when the help button is pressed. By default it is doc('uigetpref'). Note that if there is no 'HelpString' option, a button is not created. (...'ExtraOptions', eo)creates extra buttons which are not mapped to any preference settings. eo can be a string or a cell array of strings. By default it is {} and no extra buttons are created. If the user chooses one of these buttons, the dialog is closed and the string is returned in value.

(... 'DefaultButton', dbstr) sets the string value dbstr that is returned if the dialog is closed. By default, it is the first button. Note that dbstr does not have to correspond to a preference or ExtraOption.

Note If the preference does not already exist in the preference database, uigetpref creates it. Preference values are persistent and maintain their values between MATLAB sessions. Where they are stored is system dependent.

Examples This example creates the following preference dialog for the 'savefigurebeforeclosing' preference in the 'mygraphics' group.

📣 Closing Figure	
Do you want to save your figure before closing?	
You can save your figure manually by typing 'he	isave(gcf)'
	Help
Do not show this dialog again	
Yes No	Cancel

It uses the cell array {'always', 'never'; 'Yes', 'No'} to define the preference values as 'always' and 'never', and their corresponding button labels as 'Yes' and 'No'.

[selectedButton,dlgShown]=uigetpref('mygu	raphics', % Group
'savefigurebeforeclosing',	% Preference
'Closing Figure',	% Window title
{'Do you want to save your figure	before closing?'

11	
'You can save your figure manually by	<pre>typing ''hgsave(gcf)'''},</pre>
{'always','never';'Yes','No'},	% Values and button strings
'ExtraOptions','Cancel',	% Additional button
'DefaultButton','Cancel',	% Default choice
'HelpString','Help',	% String for Help button
'HelpFcn','doc(''closereq'');')	% Callback for Help button

See Also

addpref, getpref, ispref, rmpref, setpref, uisetpref

uiimport

Purpose	Open Import Wizard to import data
Syntax	uiimport uiimport(filename) uiimport('-file') uiimport('-pastespecial') S = uiimport()
Description	uiimport starts the Import Wizard in the current directory, presenting options to load data from a file or the clipboard.
	uiimport(filename) starts the Import Wizard, opening the file specified in filename. The Import Wizard displays a preview of the data in the file.
	<pre>uiimport('-file') works as above but presents the file selection dialog first.</pre>
	<pre>uiimport('-pastespecial') works as above but presents the clipboard contents first.</pre>
	S = uiimport() works as above with resulting variables stored as fields in the struct S.
	Note For ASCII data, you must verify that the Import Wizard correctly identified the column delimiter.
See Also	load importdata clipboard fileformats

See Also load, importdata, clipboard, fileformats

Purpose	Create menus on figure windows
Syntax	handle = uimenu(' <i>PropertyName</i> ',PropertyValue,) handle = uimenu(parent,' <i>PropertyName</i> ',PropertyValue,)
Description	uimenu creates a hierarchy of menus and submenus that are displayed in the figure window's menu bar. You also use uimenu to create menu items for context menus.
	handle = uimenu(' <i>PropertyName</i> ', PropertyValue,) creates a menu in the current figure's menu bar using the values of the specified properties and assigns the menu handle to handle.
	See the Uimenu Properties reference page for more information.
	handle = uimenu(parent, ' <i>PropertyName</i> ', PropertyValue,) creates a submenu of a parent menu or a menu item on a context menu specified by parent and assigns the menu handle to handle. If parent refers to a figure instead of another uimenu object or a uicontextmenu, MATLAB software creates a new menu on the referenced figure's menu bar.
Remarks	MATLAB adds the new menu to the existing menu bar. If the figure does not have a menu bar, MATLAB creates one. Each menu choice can itself be a menu that displays its submenu when selected. uimenu accepts property name/property value pairs, as well as structures and cell arrays of properties as input arguments.
	The uimenu Callback property defines the action taken when you activate the created menu item.
	Uimenus only appear in figures whose Window Style is normal. If a figure containing uimenu children is changed to modal, the uimenu children still exist and are contained in the Children list of the figure, but are not displayed until the WindowStyle is changed to normal.
	The value of the figure MenuBar property affects the content of the figure menu bar. When MenuBar is figure, a set of built-in menus precedes any user-created uimenus on the menu bar (MATLAB controls

the built-in menus and their handles are not available to the user). When MenuBar is none, uimenus are the only items on the menu bar (that is, the built-in menus do not appear).

You can set and query property values after creating the menu using set and get.

Examples This example creates a menu labeled **Workspace** whose choices allow users to create a new figure window, save workspace variables, and exit out of MATLAB. In addition, it defines an accelerator key for the Quit option.

```
f = uimenu('Label','Workspace');
    uimenu(f,'Label','New Figure','Callback','figure');
    uimenu(f,'Label','Save','Callback','save');
    uimenu(f,'Label','Quit','Callback','exit',...
    'Separator','on','Accelerator','Q');
```

See Also uicontrol, uicontextmenu, gcbo, set, get, figure

Purpose	Describe menu properties		
Modifying	You can set and query graphics object properties in two ways:		
Properties	• The Property Inspector is an interactive tool that enables you to see and change object property values. The Property inspector is available from GUIDE, or use the inspect function at the command line.		
	 The set and get commands enable you to set and query the values properties 		
	You can set default Uimenu properties on the root, figure and menu levels:		
	set(O,'DefaultUimenu <i>PropertyName</i> ',PropertyValue) set(gcf,'DefaultUimenu <i>PropertyName</i> ',PropertyValue) set(menu_handle,'DefaultUimenu <i>PropertyName</i> ',PropertyValue)		
	Where <i>PropertyName</i> is the name of the Uimenu property and PropertyValue is the value you specify as the default for that property. For more information about changing the default value of property see "Setting Default Property Values"		
Uimenu Properties	This section lists all properties useful to uimenu objects along with valid values and instructions for their use. Curly braces {} enclose default values.		
Property Name Property Description		Property Description	
	Accelerator	Keyboard equivalent	
	BeingDeleted	This object is being deleted	
	BusyAction	Callback routine interruption	
	Callback	Control action	
	Checked Menu check indicator		

Property Name	Property Description
Children	Handles of submenus
CreateFcn	Callback routine executed during object creation
DeleteFcn	Callback routine executed during object deletion
Enable	Enable or disable the uimenu
ForegroundColor	Color of text
HandleVisibility	Whether handle is accessible from command line and GUIs
Interruptible	Callback routine interruption mode
Label	Menu label
Parent	Uimenu object's parent
Position	Relative uimenu position
Separator	Separator line mode
Тад	User-specified object identifier
Туре	Class of graphics object
UserData	User-specified data
Visible	Uimenu visibility

Accelerator

character

Keyboard equivalent. An alphabetic character specifying the keyboard equivalent for the menu item. This allows users to select a particular menu choice by pressing the specified character in conjunction with another key, instead of selecting the menu item with the mouse. The key sequence is platform specific:

- For Microsoft Windows systems, the sequence is Ctrl+Accelerator. These keys are reserved for default menu items: c, v, and x.
- For UNIX systems, the sequence is **Ctrl**+Accelerator. These keys are reserved for default menu items: o, p, s, and w.

You can define an accelerator only for menu items that do not have children menus. Accelerators work only for menu items that directly execute a callback routine, not items that bring up other menus.

Note that the menu item does not have to be displayed (e.g., a submenu) for the accelerator key to work. However, the window focus must be in the figure when the key sequence is entered.

To remove an accelerator, set Accelerator to an empty string, ''.

BeingDeleted

on | {off} Read Only

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions might not need to perform actions on objects if the objects are going to be deleted, and therefore, can check the object's BeingDeleted property before acting.

BusyAction

cancel | {queue}

Callback routine interruption. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, the callback associated with the new event uses the value of BusyAction to decide whether or not to attempt to interrupt the executing callback.

- If the value is cancel, the event is discarded and the second callback does not execute.
- If the value is queue, and the Interruptible property of the first callback is on, the second callback is added to the event queue and executes in its turn after the first callback finishes execution.

Note If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. See theInterruptible property for information about controlling a callback's interruptibility.

Callback

string or function handle

Menu action. A callback routine that executes whenever you select the menu. Define this routine as a string that is a valid MATLAB expression or the name of a code file. The expression executes in the MATLAB workspace.

A menu with children (submenus) executes its callback routine before displaying the submenus. A menu without children executes its callback routine when you *release* the mouse button (i.e., on the button up event).

Checked

on | {off}

Menu check indicator. Setting this property to on places a check mark next to the corresponding menu item. Setting it to off removes the check mark. You can use this feature to create menus that indicate the state of a particular option. For example, suppose you have a menu item called **Show axes** that toggles the visibility of an axes between visible and invisible each time the user selects the menu item. If you want a check to appear next to the menu item when the axes are visible, add the following code to the callback for the **Show axes** menu item:

```
if strcmp(get(gcbo, 'Checked'),'on')
    set(gcbo, 'Checked', 'off');
else
    set(gcbo, 'Checked', 'on');
end
```

This changes the value of the Checked property of the menu item from on to off or vice versa each time a user selects the menu item.

Note that there is no formal mechanism for indicating that an unchecked menu item will become checked when selected.

Note This property is ignored for top level and parent menus.

Children

vector of handles

Handles of submenus. A vector containing the handles of all children of the uimenu object. The children objects of uimenus are other uimenus, which function as submenus. You can use this property to reorder the menus.

CreateFcn

string or function handle

Callback routine executed during object creation. The specified function executes when MATLAB creates a uimenu object. MATLAB sets all property values for the uimenu before executing the CreateFcn callback so these values are available to the callback. Within the function, use gcbo to get the handle of the uimenu being created.

Setting this property on an existing uimenu object has no effect.

You can define a default CreateFcn callback for all new uimenus. This default applies unless you override it by specifying a different CreateFcn callback when you call uimenu. For example, the code

```
set(0,'DefaultUimenuCreateFcn','set(gcbo,...
''Visible'',''on'')')
```

creates a default CreateFcn callback that runs whenever you create a new menu. It sets the default Visible property of a uimenu object.

To override this default and create a menu whose Visible property is set to a different value, call uimenu with code similar to

```
hpt = uimenu(...,'CreateFcn','set(gcbo,...
''Visible'',''off'')')
```

Note To override a default CreateFcn callback you must provide a new callback and not just provide different values for the specified properties. This is because the CreateFcn callback runs after the property values are set, and can override property values you have set explicitly in the uimenu call. In the example above, if instead of redefining the CreateFcn property for this uimenu, you had explicitly set Visible to off, the default CreateFcn callback would have set Visible back to the default, i.e., on. Do not call copyobj or textwrap (which calls copyobj) inside a CreateFcn. The act of copying the uicontrol object fires the CreateFcn repeatedly, which raises a series of error messages after exceeding the root object's RecursionLimit property.

See "Function Handle Callbacks" for information on how to use function handles to define a callback function.

DeleteFcn

string or function handle

Delete uimenu callback routine. A callback routine that executes when you delete the uimenu object (e.g., when you issue a delete command or cause the figure containing the uimenu to reset). MATLAB executes the routine before destroying the object's properties so these values are available to the callback routine.

The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which is more simply queried using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define a callback function.

Enable

{on} | off

Enable or disable the uimenu. This property controls whether a menu item can be selected. When not enabled (set to off), the menu Label appears dimmed, indicating the user cannot select it.

ForegroundColor

ColorSpec X-Windows only

Color of menu label string. This property determines color of the text defined for the Label property. Specify a color using a three-element RGB vector or one of the MATLAB predefined names. The default text color is black. See ColorSpec for more information on specifying color.

HandleVisibility

{on} | callback | off

Control access to object's handle. This property determines when an object's handle is visible in its parent's list of children. When a handle is not visible in its parent's list of children, it is not returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close. Neither is the handle visible in the parent figure's CurrentObject property. Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

- Handles are always visible when HandleVisibility is on.
- Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.
- Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

You can set the root ShowHiddenHandles property to on to make all handles visible, regardless of their HandleVisibility settings. This does not affect the values of the HandleVisibility properties.

```
Interruptible
    {on} | off
```

Callback routine interruption mode. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, that callback attempts to interrupt the first callback. MATLAB processes the callbacks according to these factors:

- The Interruptible property of the object whose callback is executing
- Whether the executing callback contains drawnow, figure, getframe, pause, or waitfor statements
- The BusyAction property of the object whose callback is waiting to execute

If the Interruptible property of the object whose callback is executing is on (the default), the callback can be interrupted. Whenever the callback calls one of the drawnow, figure, getframe, pause, or waitfor functions, the function processes any events in the event queue, including the waiting callback, before performing its defined task.

If the Interruptible property of the object whose callback is executing is off, the callback cannot be interrupted (except by certain callbacks; see the note below). The BusyAction property of the object whose callback is waiting to execute determines what happens to the callback.

Note If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. The interrupting callback starts execution at the next drawnow, figure, getframe, pause, or waitfor statement. A figure's WindowButtonDownFcn callback routine, or an object's ButtonDownFcn or Callback routine are processed according to the rules described above.

Label string

Menu label. A string specifying the text label on the menu item. You can specify a mnemonic for the label using the '&' character. Except as noted below, the character that follows the '&' in the string appears underlined and selects the menu item when you type **Alt+** followed by that character while the menu is visible. The '&' character is not displayed. To display the '&' character in a label, use two '&' characters in the string:

'O&pen selection' yields Open selection

'Save && Go' yields Save & Go

'Save&&Go' yields Save & Go

'Save& Go' yields Save& Go (the space is not a mnemonic)

There are three reserved words: default, remove, factory (case sensitive). If you want to use one of these reserved words in the Label property, you must precede it with a backslash ('\') character. For example:

'\remove' yields remove

'\default' yields default

'\factory' yields factory

Parent

handle

Uimenu's parent. The handle of the uimenu's parent object. The parent of a uimenu object is the figure on whose menu bar it displays, or the uimenu of which it is a submenu. You can move

a uimenu object to another figure by setting this property to the handle of the new parent.

Position

scalar

Relative menu position. The value of Position indicates placement on the menu bar or within a menu. Top-level menus are placed from left to right on the menu bar according to the value of their Position property, with 1 representing the left-most position. The individual items within a given menu are placed from top to bottom according to the value of their Position property, with 1 representing the top-most position.

Separator

on | {off}

Separator line mode. Setting this property to on draws a dividing line above the menu item.

Тад

string

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when constructing interactive graphics programs that would otherwise need to define object handles as global variables or pass them as arguments between callback routines. You can define Tag as any string.

Туре

string (read only)

Class of graphics object. For uimenu objects, Type is always the string 'uimenu'.

UserData

matrix

User-specified data. Any matrix you want to associate with the uimenu object. MATLAB does not use this data, but you can access it using the set and get commands.

Visible

{on} | off

Uimenu visibility. By default, all uimenus are visible. When set to off, the uimenu is not visible, but still exists and you can query and set its properties.

Purpose Convert to unsigned integer
--

Syntax	I = uint8(X)
	I = uint16(X)
	I = uint32(X)
	I = uint64(X)

Description I = uint*(X) converts the elements of array X into unsigned integers. X can be any numeric object (such as a double). The results of a uint* operation are shown in the next table.

Operation	Output Range	Output Type	Bytes per Element	Output Class
uint8	0 to 255	Unsigned 8-bit integer	1	uint8
uint16	0 to 65,535	Unsigned 16-bit integer	2	uint16
uint32	0 to 4,294,967,295	Unsigned 32-bit integer	4	uint32
uint64	0 to 18,446,744,073,709,551,615	Unsigned 64-bit integer	8	uint64

double and single values are rounded to the nearest uint* value on conversion. A value of X that is above or below the range for an integer class is mapped to one of the endpoints of the range. For example,

```
uint16(70000)
ans =
65535
```

If X is already an unsigned integer of the same class, then uint* has no effect.

You can define or overload your own methods for uint* (as you can for any object) by placing the appropriately named method in an @uint* directory within a directory on your path. Type help datatypes for the names of the methods you can overload.

Remarks

Most operations that manipulate arrays without changing their elements are defined for integer values. Examples are reshape, size, the logical and relational operators, subscripted assignment, and subscripted reference.

Some arithmetic operations are defined for integer arrays on interaction with other integer arrays of the same class (e.g., where both operands are uint16). Examples of these operations are +, -, .*, ./, . \ and .^. If at least one operand is scalar, then *, /, \, and ^ are also defined. Integer arrays may also interact with scalar double variables, including constants, and the result of the operation is an integer array of the same class. Integer arrays saturate on overflow in arithmetic.

Note Only the lower order integer data types support math operations. Math operations are not supported for int64 and uint64.

A particularly efficient way to initialize a large array is by specifying the data type (i.e., class name) for the array in the zeros, ones, or eye function. For example, to create a 100-by-100 uint64 array initialized to zero, type

I = zeros(100, 100, 'uint64');

An easy way to find the range for any MATLAB integer type is to use the intmin and intmax functions as shown here for uint32:

intmin('uint32')	intmax('uint32')
ans =	ans =
0	4294967295


See Also double, single, int8, int16, int32, int64, intmax, intmin

Purpose	Open file selection dialog box with appropriate file filters
Syntax	uiopen uiopen('MATLAB') uiopen('LOAD') uiopen('FIGURE') uiopen('SIMULINK') uiopen('EDITOR')
Description	 uiopen displays a modal file selection dialog from which a user can select a file to open. The dialog is the same as the one displayed when you select Open from the File menu in the MATLAB desktop. Selecting a file in the dialog and clicking Open does the following: Gets the file using uigetfile Opens the file in the base workspace using the open command Note A modal dialog box prevents the user from interacting with other windows before responding. For more information, see WindowStyle in the MATLAB Figure Properties.
	uiopen or uiopen('MATLAB') displays the dialog with the file filter set to all MATLAB files.
	uiopen('LOAD') displays the dialog with the file filter set to MAT-files (*.mat).
	uiopen('FIGURE') displays the dialog with the file filter set to figure files (*.fig).

 $\tt uiopen('SIMULINK') \ displays the dialog with the file filter set to model files (*.mdl).$

uiopen('EDITOR') displays the dialog with the file filter set to all MATLAB files except for MAT-files and FIG-files. All files are opened in the MATLAB Editor.

Examples Typing uiopen('figure') sets the **Files of type** field to Figures (*.fig):



See Also

uigetfile, uiputfile, uisave

Purpose	Create panel container object
Syntax	<pre>h = uipanel('PropertyName1',value1,'PropertyName2',value2,) h = uipanel(parent,'PropertyName1',value1,'PropertyName2', value2,)</pre>
Description	<pre>A uipanel groups components. It can contain user interface controls with which the user interacts directly. It can also contain axes, other uipanels, and uibuttongroups. It cannot contain ActiveX controls. h = uipanel('PropertyName1', value1, 'PropertyName2', value2,) creates a uipanel container object in a figure, uipanel, or uibuttongroup. Use the Parent property to specify the parent figure, uipanel, or uibuttongroup. If you do not specify a parent, uipane1 adds the panel to the current figure. If no figure exists, one is created. See the Uipanel PropertyName1', value1, 'PropertyName2', value2,) creates a uipanel in the object specified by the handle, parent. If you also specify a different value for the Parent property, the value of the Parent property takes precedence. parent must be a figure, uipanel, or uibuttongroup. A uipanel object can have axes, uicontrol, uipane1, and uibuttongroup objects as children. For the children of a uipanel, the Position property is interpreted relative to the uipanel. If you move the panel, the children automatically move with it and maintain their positions relative to the panel. After creating a uipanel object, you can set and query its property values using set and get.</pre>
Remarks	If you set the Visible property of a uipanel object to 'off', any child objects it contains (buttons, button groups, axes, etc.) become invisible along with the panel itself. However, doing this does <i>not</i> affect the

uipanel

settings of the Visible property of any of its child objects, even though all of them remain invisible until the uipanel's visibility is set to 'on'. uibuttongroup components also behave in this manner.

Examples

This example creates a uipanel in a figure, then creates a subpanel in the first panel. Finally, it adds a pushbutton to the subpanel. Both panels use the default Units property value, normalized. Note that default Units for the uicontrol pushbutton is pixels.

```
h = figure;
hp = uipanel('Title','Main Panel','FontSize',12,...
'BackgroundColor','white',...
'Position',[.25 .1 .67 .67]);
hsp = uipanel('Parent',hp,'Title','Subpanel','FontSize',12,...
'Position',[.4 .1 .5 .5]);
hbsp = uicontrol('Parent',hsp,'String','Push here',...
'Position',[18 18 72 36]);
```

	N _ D ×
Figure 1	<u> </u>
<u>File Edit View Insert Tools Desktop Window H</u> elp	,
🗅 🗲 🖬 🚑 🔖 🔍 약 🍽 🐙 🔲 📰 🔲 🗆	
_Main Panel	
_Subpanel	
Push here	
Push here	

See Also hgtransform, uibuttongroup, uicontrol

Uipanel Properties

Modifying Properties

You can set and query graphics object properties in two ways:

- The Property Inspector is an interactive tool that enables you to see and change object property values. The Property inspector is available from GUIDE, or use the inspect function at the command line.
- The set and get functions enable you to set and query the values of properties.

You can set default uipanel properties by typing:

```
set(h, 'DefaultUipanelPropertyName', PropertyValue...)
```

Where h can be the root handle (0), a figure handle, or a uipanel handle. *PropertyName* is the name of the uipanel property and PropertyValue is the value you specify as the default for that property.

Note Default properties you set for uipanels also apply to uibuttongroups.

For more information about changing the default value of a property see "Setting Default Property Values". For an example, see the CreateFcn property.

Uipanel Properties

This section lists all properties useful to uipanel objects along with valid values and a descriptions of their use. Curly braces {} enclose default values.

Property Name	Description
BackgroundColor	Color of the uipanel background
BeingDeleted	This object is being deleted

Property Name	Description
BorderType	Type of border around the uipanel area.
BorderWidth	Width of the panel border.
BusyAction	Interruption of other callback routines
ButtonDownFcn	Button-press callback routine
Children	All children of the uipanel
Clipping	Clipping of child axes, uipanels, and uibuttongroups to the uipanel. Does not affect child uicontrols.
CreateFcn	Callback routine executed during object creation
DeleteFcn	Callback routine executed during object deletion
FontAngle	Title font angle
FontName	Title font name
FontSize	Title font size
FontUnits	Title font units
FontWeight	Title font weight
ForegroundColor	Title font color and/or color of 2-D border line
HandleVisibility	Handle accessibility from commandline and GUIs
HighlightColor	3-D frame highlight color
HitTest	Selectable by mouse click
Interruptible	Callback routine interruption mode
Parent	Uipanel object's parent
Position	Panel position relative to parent figure or uipanel

Property Name	Description
ResizeFcn	User-specified resize routine
Selected	Whether object is selected
SelectionHighlight	Object highlighted when selected
ShadowColor	3-D frame shadow color
Тад	User-specified object identifier
Title	Title string
TitlePosition	Location of title string in relation to the panel
Туре	Object class
UIContextMenu	Associates uicontextmenu with the uipanel
Units	Units used to interpret the position vector
UserData	User-specified data
Visible	Uipanel visibility.
	Note Controls the visibility of a uipanel and of its child axes, uibuttongroups. uipanels, and child uicontrols. Setting it does not change their Visible property.

BackgroundColor ColorSpec

Color of the uipanel background. A three-element RGB vector or one of the MATLAB predefined names, specifying the background color. See the ColorSpec reference page for more information on specifying color.

BeingDeleted

on | {off} Read Only

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, an object's delete function might call other functions that act on a number of different objects. These functions might not need to perform actions on objects if the objects are going to be deleted, and therefore, can check the object's BeingDeleted property before acting.

BorderType

none | {etchedin} | etchedout | beveledin | beveledout
| line

Border of the uipanel area. Used to define the panel area graphically. Etched and beveled borders provide a 3-D look. Use the HighlightColor and ShadowColor properties to specify the border color of etched and beveled borders. A line border is 2-D. Use the ForegroundColor property to specify its color.

BorderWidth

integer

Width of the panel border. The width of the panel borders in pixels. The default border width is 1 pixel. 3-D borders wider than 3 may not appear correctly at the corners.

BusyAction

cancel | {queue}

Callback routine interruption. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, the callback associated with the new event uses the value of BusyAction to decide whether or not to attempt to interrupt the executing callback.

- If the value is cancel, the event is discarded and the second callback does not execute.
- If the value is queue, and the Interruptible property of the first callback is on, the second callback is added to the event queue and executes in its turn after the first callback finishes execution.

Note If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. See the Interruptible property for information about controlling a callback's interruptibility.

ButtonDownFcn

string or function handle

Button-press callback routine. A callback routine that executes when you press a mouse button while the pointer is in a 5-pixel wide border around the uipanel. This is useful for implementing actions to interactively modify control object properties, such as size and position, when they are clicked on (using the selectmoveresize function, for example).

If you define this routine as a string, the string can be a valid MATLAB expression or the name of a code file. The expression executes in the MATLAB workspace.

Children

vector of handles

Children of the uipanel. A vector containing the handles of all children of the uipanel. A uipanel object's children are axes, uipanels, uibuttongroups, and uicontrols. You can use this property to reorder the children.

Clipping {on} | off

Clipping mode. By default, MATLAB clips a uipanel's child axes, uipanels, and uibuttongroups to the uipanel rectangle. If you set Clipping to off, the axis, uipanel, or uibuttongroup is displayed outside the panel rectangle. This property does not affect child uicontrols which, by default, can display outside the panel rectangle.

CreateFcn

string or function handle

Callback routine executed during object creation. The specified function executes when MATLAB creates a **uipanel** object. MATLAB sets all property values for the uipanel before executing the **CreateFcn** callback so these values are available to the callback. Within the function, use gcbo to get the handle of the uipanel being created.

Setting this property on an existing uipanel object has no effect.

You can define a default CreateFcn callback for all new uipanels. This default applies unless you override it by specifying a different CreateFcn callback when you call uipanel. For example, the code

```
set(0,'DefaultUipanelCreateFcn','set(gcbo,...
''FontName'',''arial'',''FontSize'',12)')
```

creates a default CreateFcn callback that runs whenever you create a new panel. It sets the default font name and font size of the uipanel title.

Note Uibuttongroup takes its default property values from uipanel. Defining a default property for all uipanels defines the same default property for all uibuttongroups.

To override this default and create a panel whose FontName and FontSize properties are set to different values, call uipanel with code similar to

```
hpt = uipanel(...,'CreateFcn','set(gcbo,...
''FontName'',''times'',''FontSize'',14)')
```

Note To override a default CreateFcn callback you must provide a new callback and not just provide different values for the specified properties. This is because the CreateFcn callback runs after the property values are set, and can override property values you have set explicitly in the uipushtool call. In the example above, if instead of redefining the CreateFcn property for this uipanel, you had explicitly set Fontsize to 14, the default CreateFcn callback would have set FontSize back to the system dependent default.

Do not call copyobj or textwrap (which calls copyobj) inside a CreateFcn. The act of copying the uicontrol object fires the CreateFcn repeatedly, which raises a series of error messages after exceeding the root object's RecursionLimit property.

See "Function Handle Callbacks" for information on how to use function handles to define a callback function.

DeleteFcn

string or function handle

Callback routine executed during object deletion. A callback routine that executes when you delete the uipanel object (e.g., when you issue a delete command or clear the figure containing the uipanel). MATLAB executes the routine before destroying the object's properties so these values are available to the callback routine. The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

FontAngle

{normal} | italic | oblique

Character slant used in the Title. MATLAB uses this property to select a font from those available on your particular system. Setting this property to italic or oblique selects a slanted version of the font, when it is available on your system.

FontName

string

Font family used in the Title. The name of the font in which to display the Title. To display and print properly, this must be a font that your system supports. The default font is system dependent. To eliminate the need to hard code the name of a fixed-width font, which may not display text properly on systems that do not use ASCII character encoding (such as in Japan), set FontName to the string FixedWidth (this string value is case insensitive).

set(uicontrol_handle, 'FontName', 'FixedWidth')

This then uses the value of the root FixedWidthFontName property which can be set to the appropriate value for a locale from startup.m in the end user's environment. Setting the root FixedWidthFontName property causes an immediate update of the display to use the new font

FontSize

integer

Title font size. A number specifying the size of the font in which to display the Title, in units determined by the FontUnits property. The default size is system dependent.

FontUnits

inches | centimeters | normalized | {points} |pixels

Title font size units. Normalized units interpret FontSize as a fraction of the height of the uipanel. When you resize the uipanel, MATLAB modifies the screen FontSize accordingly. pixels, inches, centimeters, and points are absolute units (1 point = 1/72 inch).

FontWeight

light | {normal} | demi | bold

Weight of characters in the title. MATLAB uses this property to select a font from those available on your particular system. Setting this property to bold causes MATLAB to use a bold version of the font, when it is available on your system.

ForegroundColor

ColorSpec

Color used for title font and 2-D border line. A three-element RGB vector or one of the MATLAB predefined names, specifying the font or line color. See the ColorSpec reference page for more information on specifying color.

HandleVisibility

{on} | callback | off

Control access to object's handle. This property determines when an object's handle is visible in its parent's list of children. When a handle is not visible in its parent's list of children, it is not returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close. Neither is the handle visible in the parent figure's CurrentObject property. Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

• Handles are always visible when HandleVisibility is on.

- Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.
- Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

You can set the root ShowHiddenHandles property to on to make all handles visible, regardless of their HandleVisibility settings. This does not affect the values of the HandleVisibility properties.

HighlightColor

ColorSpec

3-D frame highlight color. A three-element RGB vector or one of the MATLAB predefined names, specifying the highlight color. See the ColorSpec reference page for more information on specifying color.

HitTest

{on} | off

Selectable by mouse click. HitTest determines if the uipanel can become the current object (as returned by the gco command and the figure CurrentObject property) as a result of a mouse click on the panel. If HitTest is off, clicking the panel sets the CurrentObject to the closest ancestor of the panel that registers HitTest. The uipanel property HandleVisibility must be 'on' for it to become the CurrentObject. If the uipanel HandleVisibility is 'off' or 'callback', or if the panel and all its ancestors have HitTest set to 'off', the figure CurrentObject is the empty matrix.

```
Interruptible
    {on} | off
```

Callback routine interruption mode. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, that callback attempts to interrupt the first callback. MATLAB processes the callbacks according to these factors:

- The Interruptible property of the object whose callback is executing
- Whether the executing callback contains drawnow, figure, getframe, pause, or waitfor statements
- The BusyAction property of the object whose callback is waiting to execute

If the Interruptible property of the object whose callback is executing is on (the default), the callback can be interrupted. Whenever the callback calls one of the drawnow, figure, getframe, pause, or waitfor functions, the function processes any events in the event queue, including the waiting callback, before performing its defined task.

If the Interruptible property of the object whose callback is executing is off, the callback cannot be interrupted (except by certain callbacks; see the note below). The BusyAction property of the object whose callback is waiting to execute determines what happens to the callback. **Note** If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. The interrupting callback starts execution at the next drawnow, figure, getframe, pause, or waitfor statement. A figure's WindowButtonDownFcn callback routine, or an object's ButtonDownFcn or Callback routine are processed according to the rules described above.

Parent

handle

Uipanel parent. The handle of the uipanel's parent figure, uipanel, or uibuttongroup. You can move a uipanel object to another figure, uipanel, or uibuttongroup by setting this property to the handle of the new parent.

Position

position rectangle

Size and location of uipanel relative to parent. The rectangle defined by this property specifies the size and location of the panel within the parent figure window, uipanel, or uibuttongroup. Specify Position as

[left bottom width height]

left and bottom are the distance from the lower-left corner of the parent object to the lower-left corner of the uipanel object. width and height are the dimensions of the uipanel rectangle, including the title. All measurements are in units specified by the Units property.

ResizeFcn

string or function handle

Resize callback routine. MATLAB executes this callback routine whenever a user resizes the uipanel and the figure Resize property is set to on, or in GUIDE, the Resize behavior option is set to Other. You can query the uipanel Position property to determine its new size and position. During execution of the callback routine, the handle to the figure being resized is accessible only through the root CallbackObject property, which you can query using gcbo.

All axes, uipanel, uitable and uicontrol objects that have their Units set to normalized automatically resize proportionally to the figure. You can define individual resize functions for any such object as needed. For example, you can use ResizeFcn to maintain a GUI layout that is not directly supported by the MATLAB Position/Units paradigm.

For example, consider a GUI layout that maintains an object at a constant height in pixels and attached to the top of the figure, but always matches the width of the figure. The following ResizeFcn accomplishes this; it keeps the uicontrol whose Tag is 'StatusBar' 20 pixels high, as wide as the figure, and attached to the top of the figure. Note the use of the Tag property to retrieve the uicontrol handle, and the gcbo function to retrieve the figure handle. Also note the defensive programming regarding figure Units, which the callback requires to be in pixels in order to work correctly, but which the callback also restores to their previous value afterwards.

```
u = findobj('Tag','StatusBar');
fig = gcbo;
old_units = get(fig,'Units');
set(fig,'Units','pixels');
figpos = get(fig,'Position');
upos = [0, figpos(4) - 20, figpos(3), 20];
set(u,'Position',upos);
set(fig,'Units',old_units);
```

You can change the figure Position from within a uipanel ResizeFcn callback; however, the ResizeFcn is not called again as a result.

A figure's uipanels resize before the figure itself does. Nested uipanels resize from inner to outer, with child ResizeFcns being called before parent ResizeFcns.

Note that the print command can cause the ResizeFcn to be called if the PaperPositionMode property is set to manual and you have defined a resize function. If you do not want your resize function called by print, set the PaperPositionMode to auto.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

See Resize Behavior for information on creating resize functions using GUIDE.

Selected

on | off (read only)

Is object selected? This property indicates whether the panel is selected. When this property is on, MATLAB displays selection handles if the SelectionHighlight property is also on. You can, for example, define the ButtonDownFcn to set this property, allowing users to select the object with the mouse.

SelectionHighlight

{on} | off

Object highlighted when selected. When the Selected property is on, MATLAB indicates the selected state by drawing four edge handles and four corner handles. When SelectionHighlight is off, MATLAB does not draw the handles.

ShadowColor

ColorSpec

3-D frame shadow color. A three-element RGB vector or one of the MATLAB predefined names, specifying the shadow color. See the ColorSpec reference page for more information on specifying color.

```
Тад
```

string

User-specified object identifier. The Tag property provides a means to identify graphics objects with a user-specified label. You can define Tag as any string.

With the findobj function, you can locate an object with a given Tag property value. This saves you from defining object handles as global variables. For example, this function call returns the handles of all children (of the specified figures) that have the Tag value 'FormatTb'.

h = findobj(figurehandles, 'Tag', 'FormatTb')

Title

string

Title string. The text displayed in the panel title. You can position the title using the TitlePosition property.

If the string value is specified as a cell array of strings or padded string matrix, only the first string of a cell array or of a padded string matrix is displayed; the rest are ignored. Vertical slash ('|') characters are not interpreted as line breaks and instead show up in the text displayed in the uipanel title.

Setting a property value to default, remove, or factory produces the effect described in "Defining Default Values". To set Title to one of these words, you must precede the word with the backslash character. For example,

```
hp = uipanel(..., 'Title', '\Default');
```

TitlePosition

{lefttop} | centertop | righttop | leftbottom |
centerbottom | rightbottom

Location of the title. This property determines the location of the title string, in relation to the uipanel.

Туре

string (read-only)

Object class. This property identifies the kind of graphics object. For uipanel objects, Type is always the string 'uipanel'.

UIContextMenu

handle

Associate a context menu with a uipanel. Assign this property the handle of a Uicontextmenu object. MATLAB displays the context menu whenever you right-click the uipanel. Use the uicontextmenu function to create the context menu.

Units

```
inches | centimeters | {normalized} | points | pixels
| characters
```

Units of measurement. MATLAB uses these units to interpret the **Position** property. For the panel itself, units are measured from the lower-left corner of the figure window. For children of the panel, they are measured from the lower-left corner of the panel.

- Normalized units map the lower-left corner of the panel or figure window to (0,0) and the upper-right corner to (1.0,1.0).
- pixels, inches, centimeters, and points are absolute units (1 point = 1/72 inch).
- Character units are characters using the default system font; the width of one character is the width of the letter x, the height of one character is the distance between the baselines of two lines of text.

If you change the value of Units, it is good practice to return it to its default value after completing your computation so as not to affect other functions that assume Units is set to the default value.

UserData

matrix

User-specified data. Any data you want to associate with the uipanel object. MATLAB does not use this data, but you can access it using set and get.

Visible

{on} | off

Uipanel visibility. By default, a uipanel object is visible. When set to 'off', the uipanel is not visible, as are all child objects of the panel. When a panel is hidden in this manner, you can still query and set its properties.

Note The value of a uipanel's Visible property determines whether its child components, such as axes, buttons, uibuttongroups, and other uipanels, are visible. However, changing the Visible property of a panel does *not* change the settings of the Visible property of its child components even though hiding the panel causes them to be hidden.

Purpose	Create push button on toolbar
Syntax	<pre>hpt = uipushtool hpt = uipushtool('PropertyName1',value1,'PropertyName2', value2,) hpt = uipushtool(ht,)</pre>
Description	hpt = uipushtool creates a push button on the uitoolbar at the top the current figure window, sets all its properties to default values, as

hpt = uipushtool creates a push button on the uitoolbar at the top of the current figure window, sets all its properties to default values, and returns a handle to the tool. If no uitoolbar exists, one is created. The uitoolbar is the parent of the uipushtool. Use the returned handle hpt to set properties of the tool. The ClickedCallback passes the handle as its first argument. The button has no icon, but its border highlights when you hover over it with the mouse cursor. Add an icon by setting CData for the tool.

hpt =

uipushtool('PropertyName1', value1, 'PropertyName2', value2,...)
, creates a uipushtool and returns a handle to it. uipushtool assigns
the specified property values, and assigns default values to the
remaining properties. You can change the property values at a later
time using the set function. You can specify properties as parameter
name/value pairs, cell arrays containing parameter names and values,
or structures with fields containing parameter names and values as
input arguments. For a complete list, see Uipushtool Properties. Type
get(hpt) to see a list of uipushtool object properties and their current
values. Type set(hpt) to see a list of uipushtool object properties that
you can set and their legal property values.

hpt = uipushtool(ht,...) creates a button with ht as a parent. ht must be a uitoolbar handle.

Uipushtools appear in figures whose Window Style is 'normal' or 'docked'. Push tools do not appear in figures with 'modal' WindowStyle. If you change the WindowStyle of a figure containing a uitoolbar and its uipushtool children to 'modal', the uipushtools continue to exist as Children of the uitoolbar. However, they do not display until you change the figure ${\tt WindowStyle}$ to 'normal' or 'docked'.

Unlike push buttons, uipushtools have no way to indicate that you have double-clicked them. That is, a double click does not set the figure SelectionType property to 'open'. Double-clicking a uipushtool simply executes its ClickedCallback twice in succession. Also, uipushtools cannot have context menus.

Examples Create a uitoolbar object and places a uipushtool object on it. Generate an icon for the tool by reading a GIF file containing a MATLAB icon. Convert the indexed image to a truecolor image before specifying it as CData.

```
h = figure('ToolBar','none');
ht = uitoolbar(h);
% Use a MATLAB icon for the tool
[X map] = imread(fullfile(...
matlabroot,'toolbox','matlab','icons','matlabicon.gif'));
% Convert indexed image and colormap to truecolor
icon = ind2rgb(X,map);
% Create a uipushtool in the toolbar
hpt = uipushtool(ht,'CData',icon,...
'TooltipString','uipushtool',...
'ClickedCallback','disp(''Hello World!'')')
```

uipushtool

🥠 Fi	igure l	No. 1							J	- D ×
Eile	Edit	⊻iew	Insert	$\underline{T}ools$	Web	Desktop	<u>W</u> indow	Help		
	<u> </u>									
Ŀ	lello									

Alternatives	You can also c	reate toolbars	with push to	ools using GUIDE.
--------------	----------------	----------------	--------------	-------------------

- See Also get | set | uicontrol | uitoggletool | uitoolbar | Uipushtool Properties
- **Tutorials** "GUI with Axes, Menu, and Toolbar"
- **How To** "Creating Toolbars"

Uipushtool Properties

	Purpose	Describe push tool properties
--	---------	-------------------------------

Modifying Properties

You can set and query graphics object properties in two ways:

- The Property Inspector is an interactive tool that enables you to see and change object property values. The Property inspector is available from GUIDE, or use the inspect function at the command line.
- The set and get functions enable you to set and query the values of properties.

You can set default Uipushtool properties by typing:

set(h, 'DefaultUipushtoolPropertyName', PropertyValue...)

Where h can be the root handle (0), a figure handle, a uitoolbar handle, or a uipushtool handle. *PropertyName* is the name of the Uipushtool property and PropertyValue is the value you specify as the default for that property.

For more information about changing the default value of a property see Setting Default Property Values.

Uipushtool Properties

This section lists all properties useful to uipushtool objects along with valid values and a descriptions of their use. Curly braces {} enclose default values.

Property	Purpose
BeingDeleted	This object is being deleted.
BusyAction	Callback routine interruption.
CData	Truecolor image displayed on the control.
ClickedCallback	Control action.
CreateFcn	Callback routine executed during object creation.
DeleteFcn	Delete uipushtool callback routine.

Property	Purpose
Enable	Enable or disable the uipushtool.
HandleVisibility Control access to object's handle.	
HitTest	Whether selectable by mouse click
Interruptible	Callback routine interruption mode.
Parent	Handle of uipushtool's parent.
Separator	Separator line mode
Тад	User-specified object label.
TooltipString	Content of object's tooltip.
Туре	Object class.
UIContextMenu	Uicontextmenu object associated with the uipushtool
UserData	User specified data.
Visible	Uipushtool visibility.

BeingDeleted

on | {off} (read only)

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB software sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property). It remains set to on while the delete function executes, after which the object no longer exists.

For example, some functions may not need to perform actions on objects that are being deleted, and therefore, can check the object's BeingDeleted property before acting. BusyAction cancel | {queue}

Callback routine interruption. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, the callback associated with the new event uses the value of BusyAction to decide whether or not to attempt to interrupt the executing callback.

- If the value is cancel, the event is discarded and the second callback does not execute.
- If the value is queue, and the Interruptible property of the first callback is on, the second callback is added to the event queue and executes in its turn after the first callback finishes execution.

Note If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. See the Interruptible property for information about controlling a callback's interruptibility.

CData

3-dimensional array

Truecolor image displayed on control. An *n*-by-*m*-by-3 array of RGB values that defines a truecolor image displayed on either a push button or toggle button. Each value must be between 0.0 and 1.0. If your CData array is larger than 16 in the first or second dimension, it may be clipped or cause other undesirable effects. If the array is clipped, only the center 16-by-16 part of the array is used.

ClickedCallback

string or function handle

Control action. A routine that executes when the uipushtool's Enable property is set to on, and you press a mouse button while the pointer is on the push tool itself or in a 5-pixel wide border around it.

CreateFcn

string or function handle

Callback routine executed during object creation. The specified function executes when MATLAB creates a uipushtool object. MATLAB sets all property values for the uipushtool before executing the CreateFcn callback so these values are available to the callback. Within the function, use gcbo to get the handle of the push tool being created.

Setting this property on an existing uipushtool object has no effect.

You can define a default CreateFcn callback for all new uipushtools. This default applies unless you override it by specifying a different CreateFcn callback when you call uipushtool. For example, the code

```
imga(:,:,1) = rand(20);
imga(:,:,2) = rand(20);
imga(:,:,3) = rand(20);
set(0,'DefaultUipushtoolCreateFcn','set(gcbo,''Cdata'',imga)')
```

creates a default CreateFcn callback that runs whenever you create a new push tool. It sets the default image imga on the push tool.

To override this default and create a push tool whose Cdata property is set to a different image, call uipushtool with code similar to

```
a = [.05:.05:0.95];
imgb(:,:,1) = repmat(a,19,1)';
imgb(:,:,2) = repmat(a,19,1);
imgb(:,:,3) = repmat(flipdim(a,2),19,1);
hpt = uipushtool(...,'CreateFcn','set(gcbo,''CData'',imgb)',...)
```

Note To override a default CreateFcn callback you must provide a new callback and not just provide different values for the specified properties. This is because the CreateFcn callback runs after the property values are set, and can override property values you have set explicitly in the uipushtool call. In the example above, if instead of redefining the CreateFcn property for this push tool, you had explicitly set CData to imgb, the default CreateFcn callback would have set CData back to imga.

Do not call copyobj or textwrap (which calls copyobj) inside a CreateFcn. The act of copying the uicontrol object fires the CreateFcn repeatedly, which raises a series of error messages after exceeding the root object's RecursionLimit property.

See "Function Handle Callbacks" for information on how to use function handles to define a callback function.

DeleteFcn

string or function handle

Callback routine executed during object deletion. A callback routine that executes when you delete the uipushtool object (e.g., when you call the delete function or cause the figure containing the uipushtool to reset). MATLAB executes the routine before destroying the object's properties so these values are available to the callback routine.

The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define a callback function.

Enable

{on} | off

Enable or disable the uipushtool. This property controls how uipushtools respond to mouse button clicks, including which callback routines execute.

- on The uipushtool is operational (the default).
- off The uipushtool is not operational and its image (set by the Cdata property) is grayed out.

When you left-click a uipushtool whose Enable property is on, MATLAB performs these actions in this order:

- 1 Executes the push tool's ClickedCallback routine.
- **2** Does *not* set the figure CurrentPoint property and does not execute the figure's WindowButtonDownFcn callback.
- **3** Does not set the figure SelectionType property.

When you left-click a uipushtool whose Enable property is off, or when you right-click a uipushtool whose Enable property has any value, no action is reported, no callback executes, and neither the SelectionType nor CurrentPoint figure properties are modified.

HandleVisibility

{on} | callback | off

Control access to object's handle. This property determines when an object's handle is visible in its parent's list of children. When a handle is not visible in its parent's list of children, it is not returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close. Neither is the handle visible in the parent figure's CurrentObject property. Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

- Handles are always visible when HandleVisibility is on.
- Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.
- Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

You can set the root ShowHiddenHandles property to on to make all handles visible, regardless of their HandleVisibility settings. This does not affect the values of the HandleVisibility properties.

HitTest

{on} | off

Selectable by mouse click. This property has no effect on uipushtool objects.

```
Interruptible
    {on} | off
```

Callback routine interruption mode. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, that callback attempts to interrupt the first callback. MATLAB processes the callbacks according to these factors:

- The Interruptible property of the object whose callback is executing
- Whether the executing callback contains drawnow, figure, getframe, pause, or waitfor statements
- The BusyAction property of the object whose callback is waiting to execute

If the Interruptible property of the object whose callback is executing is on (the default), the callback can be interrupted. Whenever the callback calls one of the drawnow, figure, getframe, pause, or waitfor functions, the function processes any events in the event queue, including the waiting callback, before performing its defined task.

If the Interruptible property of the object whose callback is executing is off, the callback cannot be interrupted (except by certain callbacks; see the note below). The BusyAction property of the object whose callback is waiting to execute determines what happens to the callback.

Note If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. The interrupting callback starts execution at the next drawnow, figure, getframe, pause, or waitfor statement. A figure's WindowButtonDownFcn callback routine, or an object's ButtonDownFcn or Callback routine are processed according to the rules described above.

Parent

handle

Uipushtool parent. The handle of the uipushtool's parent toolbar. You can move a uipushtool object to another toolbar by setting this property to the handle of the new parent.

Separator

on | {off}

Separator line mode. Setting this property to on draws a dividing line to the left of the uipushtool.

Тад

string

User-specified object identifier. The Tag property provides a means to identify graphics objects with a user-specified label. You can define Tag as any string.

With the findobj function, you can locate an object with a given Tag property value. This saves you from defining object handles as global variables. For example, this function call returns the handles of all children (of the specified toolbars) that have the Tag value 'Copy'.

h = findobj(uitoolbarhandles, 'Tag', 'Copy')

TooltipString

string

Content of tooltip for object. The TooltipString property specifies the text of the tooltip associated with the uipushtool. When the user moves the mouse pointer over the control and leaves it there, the tooltip is displayed.

To create a tooltip that has more than one line of text, use sprintf to generate a string containing newline (\n) characters and then set the TooltipString to that value. For example:

h = uipushtool; s = sprintf('Pushtool tooltip line 1\nPushtool tooltip line 2');

set(h, 'TooltipString',s)

Туре

string (read-only)

Object class. This property identifies the kind of graphics object. For uipushtool objects, Type is always the string 'uipushtool'.

UIContextMenu

handle

Associate a context menu with uicontrol. This property has no effect on uipushtool objects.

UserData

array

User specified data. You can specify UserData as any array you want to associate with the uipushtool object. The object does not use this data, but you can access it using the set and get functions.

Visible

{on} | off

Uipushtool visibility. By default, all uipushtools are visible. When set to off, the uipushtool is not visible, but still exists and you can query and set its properties.

uiputfile

Purpose	Open standard dialog box for saving files
Syntax	<pre>FileName = uiputfile [FileName,PathName] = uiputfile [FileName,PathName,FilterIndex] = uiputfile(FilterSpec) [FileName,PathName,FilterIndex] = uiputfile(FilterSpec, DialogTitle) [FileName,PathName,FilterIndex] = uiputfile(FilterSpec, DialogTitle,DefaultName)</pre>
Description	FileName = uiputfile displays a modal dialog box for selecting or specifying a file you want to create or save. The dialog box lists the files and folders in the current folder. If the selected or specified filename is valid, uiputfile returns it in FileName.
	[FileName,PathName] = uiputfile works the same as the first syntax, but also returns the path to FileName in PathName, or if you cancel the dialog, returns 0 for both arguments. If you do not provide any output arguments, the filename alone is returned in ans.
	<pre>[FileName,PathName,FilterIndex] = uiputfile(FilterSpec) displays only those files with extensions that match FilterSpec. On some platforms uiputfile also displays the files that do not match FilterSpec in grey. The uiputfile function appends 'All Files' to the list of file types. FilterSpec can be a string or a cell array of strings, and can include the * and ? wildcard characters. For example, '*.m' lists all MATLAB program files in a folder.</pre>
	FilterSpec can be a string that contains a filename. uiputfile displays the filename selected in the File name field and uses the file extension as the default filter. The FilterSpec string can include a path, or consist of a path only. To specify a folder only, make the last character in DefaultName '\' or '/'. A path can contain special path characters, such as '.', '', '/', '\', or '~'. For example, '/*.m' lists all program files in the folder above the current folder. If FilterSpec is a cell array of strings, the first column contains a list of file extensions. The optional second column contains a corresponding list of descriptions. These descriptions replace the default descriptions

in the **Save as type** pop-up menu. A description cannot be an empty string. See the "Examples" on page 2-4215 for illustration of using cell arrays as FilterSpec. If you do not specify FilterSpec, uiputfile uses the default list of file types (all MATLAB files). FilterIndex is the index of the filter selected in the dialog box. Indexing starts at 1. If you click the **Cancel** button, close the dialog window, or if the file does not exist, uiputfile returns FilterIndex as 0.

[FileName,PathName,FilterIndex] =

uiputfile(FilterSpec,DialogTitle) displays a dialog box that has the title DialogTitle. To use the default file types and to specify a dialog title, enter uiputfile('', 'DialogTitle')

[FileName,PathName,FilterIndex] =

uiputfile(FilterSpec,DialogTitle,DefaultName) displays a dialog box in which the filename specified by DefaultName appears in the File name field. DefaultName can also be a path or a path+filename. To specify a folder only, make the last character in DefaultName '\' or '/'. In this case, uiputfile opens the dialog box in the folder specified by the path. If you specify a path in DefaultName that does not exist, uiputfile opens the dialog box in the current folder. You can use '.','...', '\', '/', or ~ in the DefaultName argument.

When typing into the dialog box, if you include either of the wildcard characters '*' or '?' in a file name, uiputfile does not respond to clicking **Save**. The dialog box remains open until you cancel it or remove the wildcard characters. This restriction applies to all platforms, even to file systems that permit these characters in file names.

If you select or specify an existing filename, the following warning dialog box opens.

Save fil	e name	×	
1	D:\Work\untitled1.m already exists. Do you want to replace it?		
	Yes No		

Select **Yes** to replace the existing file or **No** to return to the dialog to select another filename. Selecting **Yes** returns the name of the file. Selecting **No** returns 0.

Successful execution of uiputfile does not create a file; it only returns the name of a new or existing file that you designate.

For Microsoft Windows platforms, the dialog box is the Windows dialog box native to your platform, and thus can differ from what you see in the examples that follow.

For UNIX platforms, the dialog box is like the one shown in the following figure.

	Select File to	Write
Save In: 🗀 MATLABFile	es	- 🖻 🖄 🍱 🗄
 custhelp databasetoolboxfiles matlab_files mymfiles published quick_ref_training collatznew.m Contents.m fileassoc.m 	 help_locator.m loopcountfile.m matlab.mat myfcn.m newprofile.m newprofilehelp.m oldprofile.m oldprofilehelp.m oldprofilehelp.m outputtest.m 	■ pythag.m ■ rtw_solver_tp.m
File <u>N</u> ame: Files of <u>Ty</u> pe: MATLAB	files	Save Cancel

For Mac platforms, the dialog box is like the one shown in the following figure.


uiputfile

📁 work	•
Name	Date Modified
🖞 dolphin.gif	Wednesday, November 15, 2006 5:03 PM
onek.ps	Wednesday, November 15, 2006 4:52 PM
onek2.ps	Wednesday, November 15, 2006 4:52 PM
onekc.ps	Wednesday, November 15, 2006 4:52 PM
onekc2.ps	Wednesday, November 15, 2006 4:52 PM
🖞 ps3file.ps	Wednesday, November 15, 2006 4:37 PM
psc2file.ps	Wednesday, November 15, 2006 4:38 PM
pscfile.ps	Wednesday, November 15, 2006 4:38 PM
psfile.ps	Wednesday, November 15, 2006 4:37 PM
tp380702	Thursday, November 16, 2006 9:42 AM
File Format: All F	ïles 🛟

Note A modal dialog box prevents you from interacting with other MATLAB windows before responding. To block MATLAB program execution as well, use the uiwait function. For more information about modal dialog boxes, see WindowStyle in the MATLAB Figure Properties.

Examples The following statement displays a dialog box titled 'Save file name', setting the **Filename** field to animinit.m and the filter to program files (*.m). Because FilterSpec is a string, the filter also includes All Files (*.*)

```
[file,path] = uiputfile('animinit.m','Save file name');
```




The following statement displays a dialog box titled 'Save Workspace As' with the filter specifier set to MAT-files.

```
[file,path] = uiputfile('*.mat', 'Save Workspace As');
```

Save Workspace	As				? ×
Save jn:	C Work		•	+ 🗈 💣 🎟	
Desktop Desktop My Documents My Computer My Network Places	Ø var1.mat				
	File <u>n</u> ame: Save as <u>t</u> ype:	*.mat [MAT-files (*.mat)		-	<u>S</u> ave Cancel

To display several file types in the **Save as type** list box, separate each file extension with a semicolon, as in the following code. uiputfile displays a default description for each known file type, such as "Model files" for Simulink .mdl files.


```
[filename, pathname] = uiputfile(...
{'*.m';'*.mdl';'*.mat';'*.*'},...
'Save as');
```



If you want to create a list of file types and give them descriptions that are different from the defaults, use a cell array. This example also associates multiple file types with the 'MATLAB Files' description.

```
[filename, pathname, filterindex] = uiputfile( ...
{'*.m;*.fig;*.mat;*.mdl','MATLAB Files (*.m,*.fig,*.mat,*.mdl)';
'*.m', 'program files (*.m)';...
'*.fig','Figures (*.fig)';...
'*.mat','MAT-files (*.mat)';...
'*.mdl','Models (*.mdl)';...
'*.*', 'All Files (*.*)'},...
'Save as');
```

The first column of the cell array contains the file extensions, while the second contains the descriptions you want to provide for the file types. The first entry of column one contains several extensions separated by semicolons. These file types all associate with the description 'MATLAB Files (*.m,*.fig,*.mat,*.mdl)'. The code produces the dialog box shown in the following figure.



The following code checks for the existence of the file and displays a message about the result of the file selection operation.

```
[filename, pathname] = uiputfile('*.m','Pick a MATLAB program file'
if isequal(filename,0) || isequal(pathname,0)
    disp('User selected Cancel')
```

uiputfile

```
else
    disp(['User selected',fullfile(pathname,filename)])
end
```

Select or enter a file name for saving a figure as an image in one of four formats, described in a cell array.

```
uiputfile({'*.jpg;*.tif;*.png;*.gif','All Image Files';...
'*.*','All Files' },'Save Image',...
'C:\Work\newfile.jpg')
```



See Also

save, uigetdir, uigetfile, uisave

"Files and Filenames"

uiresume

Purpose	Resume execution of blocked M-file
Syntax	uiresume(h)
Description	uiresume(h) resumes the M-file execution that uiwait suspended.
Remarks	The uiwait and uiresume functions block and resume MATLAB program execution. When creating a dialog, you should have a uicontrol component with a callback that calls uiresume or a callback that destroys the dialog box. These are the only methods that resume program execution after the uiwait function blocks execution.
	When used in conjunction with a modal dialog, uiresume can resume the execution of the M-file that uiwait suspended while presenting a dialog box.
Example	This example creates a GUI with a Continue push button. The example calls uiwait to block MATLAB execution until uiresume is called. This happens when the user clicks the Continue push button because the push button's Callback callback, which responds to the click, calls uiresume.
	<pre>f = figure; h = uicontrol('Position',[20 20 200 40],'String','Continue', 'Callback','uiresume(gcbf)'); disp('This will print immediately'); uiwait(gcf); disp('This will print after you click Continue'); close(f);</pre>
	gcbf is the handle of the figure that contains the object whose callback is executing.

"Using a Modal Dialog Box to Confirm an Operation" is a more complex example for a GUIDE GUI. See "Icon Editor" for an example for a programmatically created GUI.

uiresume

See Also dialog, figure, uicontrol, uimenu, uiwait, waitfor

Purpose	Open standard dialog box for saving workspace variables
Syntax	uisave uisave(variables) uisave(variables,filename) uisave(variables) uisave(variables,filename)
Description	uisave displays the Save Workspace Variables dialog box for

tion uisave displays the Save Workspace Variables dialog box for saving workspace variables to a MAT-file, as shown in the following figure. The dialog box opens in your current folder. Navigate to the folder in which you want to save the MAT-file.

Save Worksp	ace Variables				? X
Save in: 🔂	Work	-	🗢 🔁	💣 🎞 •	
, File <u>n</u> ame:	[Sav	
_					
Save as type:	MAT-files (*.mat)		•	Cano	el

If you type a name in the **File name** field, such as my_vars, and click **Save**, the dialog saves all workspace variables to the file my_vars.mat. The default filename is matlab.mat. If the filename you specify exists in that folder, uisave prompts you and gives you a chance to cancel the operation.

uisave(variables) saves only the variables listed in variables. For a single variable, variables can be a string. For more than one variable, variables must be a cell array of strings.

	uisave(variables,filename) uses the specified filename as the default File name in the Save Workspace Variables dialog box.
	If you type a name in the File name field, such as my_vars, and click Save , the dialog saves all workspace variables in the file my_vars.mat. The default filename is matlab.mat.
	uisave(variables) saves only the variables listed in variables. For a single variable, variables can be a string. For more than one variable, variables must be a cell array of strings.
	uisave(variables,filename) uses the specified filename as the default File name in the Save Workspace Variables dialog box.
	The following GUI options also save workspace variables:
	• Use File > Save to save workspace variables.
	• Click the Save icon in the Workspace Browser.
	• Select one or more variables in the Workspace Browser, right-click, and choose Save as from the context menu.
	Note The uisave dialog box is modal. A modal dialog box prevents the user from interacting with other windows before responding. For more information, see WindowStyle in the MATLAB Figure Properties.
Example	This example creates workspace variables h and g, and then displays the Save Workspace Variables dialog box in the current folder with the default File name set to var1.
	h = 365; g = 52; uisave({'h','g'},'var1');

Save Workspace	. Variables				? ×
Save jn:	C Work		•	🗕 🖻 💣 🎟	
Desktop Desktop My Documents					
My Computer					
My Network Places					
	File <u>n</u> ame:	var1		-	<u>S</u> ave
	Save as <u>t</u> ype:	MAT-files (*.mat)		•	Cancel

Clicking **Save** stores the workspace variables h and g in the file var1.mat in the displayed folder.

See Also save, uigetfile, uiputfile, uiopen

"Saving the Current Workspace"

uisetcolor

Purpose	Open standard dialog box for setting object's ColorSpec
Syntax	<pre>c = uisetcolor c = uisetcolor([r g b]) c = uisetcolor(h) c = uisetcolor(,'dialogTitle')</pre>
Description	c = uisetcolor displays a modal color selection dialog appropriate to the platform, and returns the color selected by the user. The dialog box is initialized to white.
	<pre>c = uisetcolor([r g b]) displays a dialog box initialized to the specified color, and returns the color selected by the user. r, g, and b must be values between 0 and 1.</pre>
	c = uisetcolor(h) displays a dialog box initialized to the color of the object specified by handle h, returns the color selected by the user, and applies it to the object. h must be the handle to an object containing a color property.
	<pre>c = uisetcolor(, 'dialogTitle') displays a dialog box with the specified title.</pre>
	If the user presses Cancel from the dialog box, or if any error occurs, the output value is set to the input RGB triple, if provided; otherwise, it is set to 0.
	Note A modal dialog box prevents the user from interacting with other windows before responding. For more information, see WindowStyle in the MATLAB Figure Properties.
See Also	ColorSpec

Purpose	Open standard dialog box for setting object's font characteristics
Syntax	uisetfont uisetfont(h) uisetfont(S) uisetfont(,'DialogTitle') S = uisetfont()
Description	uisetfont enables you to change font properties (FontName, FontUnits, FontSize, FontWeight, and FontAngle) for a text, axes, or uicontrol object. The function returns a structure consisting of font properties and values. You can specify an alternate title for the dialog box.
	uisetfont displays a modal dialog box and returns the selected font properties.
	Note A modal dialog box prevents the user from interacting with other windows before responding. For more information, see WindowStyle in the MATLAB Figure Properties.
	uisetfont(h) displays a modal dialog box, initializing the font property values with the values of those properties for the object whose handle is h. Selected font property values are applied to the current object. If a second argument is supplied, it specifies a name for the dialog box.
	<pre>uisetfont(S) displays a modal dialog box, initializing the font property values with the values defined for the specified structure (S). S must define legal values for one or more of these properties: FontName, FontUnits, FontSize, FontWeight, and FontAngle and the field names must match the property names exactly. If other properties are defined, they are ignored. If a second argument is supplied, it specifies a name for the dialog box.</pre>

uisetfont

	<pre>uisetfont(, 'DialogTitle') displays a modal dialog box with the title DialogTitle and returns the values of the font properties selected in the dialog box. S = uisetfont() returns the properties FontName, FontUnits, FontSize, FontWeight, and FontAngle as fields in a structure. If the user presses Cancel from the dialog box or if an error occurs, the output value is set to 0.</pre>
Example	<pre>These statements create a text object, then display a dialog box (labeled Update Font) that enables you to change the font characteristics: h = text(.5,.5, 'Figure Annotation'); uisetfont(h, 'Update Font') These statements create two push buttons, then set the font properties of one based on the values set for the other: % Create push button with string ABC c1 = uicontrol('Style', 'pushbutton', 'Position', [10 10 100 20], 'String', 'ABC'); % Create push button with string XYZ c2 = uicontrol('Style', 'pushbutton', 'Position', [10 50 100 20], 'String', 'XYZ'); % Display set font dialog box for c1, make selections, & and save to d d = uisetfont(c1); % Apply those settings to c2 set(c2, d)</pre>
See Also	axes, text, uicontrol

Purpose Manage preferences used in uigetpref

Syntax uisetpref('clearall')

Description uisetpref('clearall') resets the value of all preferences registered through uigetpref to 'ask'. This causes the dialog box to display when you call uigetpref.

Note Use setpref to set the value of a particular preference to 'ask'.

See Also setpref, uigetpref

uistack

Purpose	Reorder visual stacking order of objects
Syntax	uistack(h) uistack(h, <i>stackopt</i>) uistack(h, <i>stackopt</i> ,step)
Description	uistack(h) raises the visual stacking order of the objects specified by the handles in h by one level (step of 1). All handles in h must have the same parent.
	<pre>uistack(h,stackopt) moves the objects specified by h in the stacking order, where stackopt is one of the following:</pre>
	• 'up' – moves h up one position in the stacking order
	• 'down' – moves h down one position in the stacking order
	 'top' – moves h to the top of the current stack
	• <code>'bottom'</code> – moves h to the bottom of the current stack
	uistack(h, <i>stackopt</i> ,step) moves the objects specified by h up or down the number of levels specified by step.
	Note In a GUI, axes objects are always at a lower level than uicontrol objects. You cannot stack an axes object on top of a uicontrol object.
	See "Setting Tab Order" in the MATLAB documentation for information about changing the tab order.
Example	The following code moves the child that is third in the stacking order of the figure handle hObject down two positions.
	<pre>v = allchild(hObject) uistack(v(3),'down',2)</pre>

Purpose	Create 2-D graphic table GUI component
Syntax	<pre>uitable uitable('PropertyName1', value1,'PropertyName2',value2,) uitable(parent,) handle = uitable()</pre>
Description	uitable creates an empty uitable object in the current figure window, using default property values. If no figure exists, a new figure window opens.
	uitable('PropertyName1', value1,'PropertyName2',value2,) creates a uitable object with specified property values. Properties that you do not specify assume the default property values. See the Uitable Properties reference page for information about the available properties.
	uitable(parent,) creates a uitable object as a child of the specified parent handle parent. The parent can be a figure or uipanel handle. If you also specify a different value for the Parent property, the value of the Parent property takes precedence.
	<pre>handle = uitable() creates a uitable object and returns its handle.</pre>
Tips	After creating a uitable object, you can set and query its property values using the set and get functions.
	If the ColumnEditable property is true for columns you edit, you can change values in a displayed table. By default, this property is false for all columns. If a noneditable column contains pop-up choices, only the current choice is visible (and not the pop-up menu control).

If you attempt to create a uitable object when running MATLAB on a UNIX¹⁸ system without a Java virtual machine (matlab -nojvm) or without a display (matlab nodisplay), no table generates and you receive an error.

The **CellEditCallback** executes after you edit a value and do any of the following:

- Type Enter.
- Click another table cell.
- Click anywhere else within the table.
- Click another control or area within the same figure window.
- Click another window, click again on the GUI containing the table (or use **Alt+Tab** to switch windows), and then perform any of the above four actions.

When the CellEditCallback callback executes, uitable updates the underlying data matrix (the table Data property) to contain the value that the cell now displays.

The **CellSelectionCallback** executes when you select a table cell or remove one from the current selection by **Ctrl**+clicking it. Clicking a cell without pressing any key selects it and deselects all currently selected cells. You can define a range of table cells by **Shift**+clicking an unselected cell after selecting one or more cells. The callback provides event data that identifies the rows and columns of all cells in the current selection.

You cannot select table cells programmatically. Directly clicking cells is the only method of selection.

Examples Create a table, provide magic-square data, set column widths uniformly, and specify the uitable ColumnWidth property as a cell array:

18. UNIX is a registered trademark of The Open Group in the United States and other countries.

1 Create a table in the current figure. If no figure exists, one opens:

```
Figure 1

File

Edit

View

Image: Contraction of the second of the
```

2 As the table has no content (its Data property is empty), it initially displays no rows or columns. Provide data (a magic square)

set(t,'Data',magic(10))

t = uitable;

uitable

Fi	igure	1			. 0		
			Insert	Tools	Desktop	Window	Help
Γ		1		2		3	4
	1		92		99	1	
L	2		98		80	7	
L	3		4		81	88	
L	4		85		87	19	
	5		86		93	25	
L	6		17		24	76	
L	7		23		5	82	
L	8		79		6	13	
L	9		10		12	94	
	10		11		18	100	
Γ							
	П	d –		- [Þ
		·					

3 Make the entire table contents visible. Set column widths to 25 pixels uniformly. Specify the ColumnWidth property of the table as a cell array.

```
set(t, 'ColumnWidth', {25})
```

igur Edi			Insert	- To	ols	Deski	ton	Wind	0141	Help
	c vic		moore		,013	DOSN	.op	*****	011	noip
	1	2	3	4	5	6	7	8	9	10
1	92	99	1	8	15	67	74	51	58	40
2	98	80 81	7	14	16	73	55	57	64	41
3	4	⁸ 1	88	20	22	54	56	63	70	47
4	85	87	19	21	3	60	62	69	71	28
5	86	93	25	2	9	61	68	75	52	34
6	17	24	76	83	90	42	49	26	33	65
7	23			89	91	48	30	32	39	66
8	79	6		95	97	29	31	38	45	
9	10	12		96	78	35	37	44	46	53
10	11	18	100	-77	84	36	43	50	27	59

Cell arrays that specify ColumnWidth can contain:

- One number (a width measured in pixels, as shown here) or the string 'auto'.
- A cell array containing a list of pixel sizes having up to as many entries as the table has columns .

If a list of column widths has n entries, where n is smaller than the number of columns, it sets the first n column widths only. You can substitute 'auto' for any value in the cell array to have the width of that column calculated automatically.

Create a figure and add a table to contain a 3-by-3 data matrix. The code specifies the column names, row names, parent, and position of the table:

```
f = figure('Position',[200 200 400 150]);
dat = rand(3);
cnames = {'X-Data','Y-Data','Z-Data'};
rnames = {'First','Second','Third'};
t = uitable('Parent',f,'Data',dat,'ColumnName',cnames,...
'RowName',rnames,'Position',[20 20 360 100]);
```

4	Fig	ure 1		_	
File	E	dit View Inse	rt Tools Deskt	op Window He	elp 🛥
1	6	i 🛃 🍯	📐 🔍 🔍	👋 🕲 🔏	, »
		X-Data	Y-Data	Z-Data	
	1	0.8147	0.9134	0.2785	
	2	0.9058	0.6324	0.5469	
	3	0.1270	0.0975	0.9575	

Create a table to contain a 3-by-4 array that contains numeric, logical, and string data, as follows:

- First column (Rate): Numeric, with three decimals (not editable)
- Second column (Amount): Currency (not editable)
- Third column (Available): Check box (editable)
- Fourth column (**Fixed/Adj**): Pop-up menu with two choices: Fixed and Adjustable (editable)

• Specify the RowName property as empty to remove row names from the table.

```
f = figure('Position',[100 100 400 150]);
dat = {6.125, 456.3457, true, 'Fixed';...
6.75, 510.2342, false, 'Adjustable';...
7, 658.2, false, 'Fixed';};
columnname = {'Rate', 'Amount', 'Available', 'Fixed/Adj'};
columnformat = {'numeric', 'bank', 'logical', {'Fixed' 'Adjustable'
columneditable = [false false true true];
t = uitable('Units', 'normalized', 'Position',...
[0.1 0.1 0.9 0.9], 'Data', dat,...
'ColumnName', columnname,...
'ColumnFormat', columnformat,...
'ColumnEditable', columneditable,...
'RowName',[]);
```

📣 Fig	jure 1					×
File	Edit V	/iew Insert T	ools Desktop	Window He	þ	ъ
		Rate	Amount	Available	Fixed/Adj	
	1	6.1250	456.35	•	Fixed 💽	
	2	6.7500	510.23		Adjusta 💽	
	3	7	658.20		Fixed 💽	

- **Alternatives** You can add tables to GUIs you create with "Defining Tables".
- **See Also** figure | format | get | set | uipanel | Uitable Properties
- **Tutorials** "GUI to Interactively Explore Data in a Table"

uitable

• "GUI that Displays and Graphs Tabular Data"

How To • "Defining Tables"

Purpose Describe table properties

Modifying Properties

You can set and query graphics object properties in two ways:

- The Property Inspector is an interactive tool that enables you to see and change object property values. The Property inspector is available from GUIDE, or use the inspect function at the command line.
- The set and get functions enable you to set and query the values of properties.

You can set default uitable properties by typing:

set(h, 'DefaultUitablePropertyName', PropertyValue...)

Where h can be the root handle (0), a figure handle, or a uitable handle. *PropertyName* is the name of the uitable property and PropertyValue is the value you specify as the default for that property.

For more information about changing the default value of a property see "Setting Default Property Values". For an example, see the CreateFcn property.

Uitable Properties

This section lists all properties useful to uitable objects along with valid values and descriptions of their use. In the property descriptions, curly braces {} enclose default values.

Property Name	Description
BackgroundColor	Background color of cells.
BeingDeleted	This object is being deleted.
BusyAction	Callback routine interruption
ButtonDownFcn	Button-press callback routine

Property Name	Description
CellEditCallback	Callback when data in a cell is changed.
CellSelectionCallbac	Callback when cell is selected
Children	uitable objects have no children
Clipping	Does not apply to uitable objects
ColumnEditable	Determines data in a column as editable
ColumnFormat	Determines display and editablility of columns
ColumnName	Column header label
ColumnWidth	Width of each column in pixels
CreateFcn	Callback routine during object creation
Data	Table data
DeleteFcn	Callback routine during object deletion
Enable	Enable or disable the uitable
Extent	Size of uitable rectangle
FontAngle	Character slant of cell content
FontName	Font family for cell content
FontSize	Font size of cell content
FontUnits	Font size units for cell content
FontWeight	Weight of cell text characters
ForegroundColor	Color of text in cells
HandleVisibility	Control access to object's handle
HitTest	Selectable by mouse click
Interruptible	Callback routine interruption mode
KeyPressFcn	Key press callback function

Property Name	Description
Parent	uitable parent
Position	Size and location of uitable
RearrangeableColumn	Location of the column
RowName	Row header label names
RowStriping	Color striping of label rows
Selected	Is object selected?
SelectionHighlight	Object highlight when selected
Тад	Use-specified object label
TooltipString	Content of tooltip for object
Туре	Class of graphics object
UIContextMenu	Associate context menu with uitable
Units	Units of measurement
UserData	User-specified data
Visible	uitable visibility

BackgroundColor

1-by-3 or 2-by-3 matrix of RGB triples

Cell background color. Color used to fill the uitable cells. Specify as an 1-by-3 or 2-by-3 matrix of RGB triples, such as [.8 .9. .8] or [1 1 .9; .9 1 1]. Each row is an RGB triplet of real numbers between 0.0 and 1.0 that defines one color. (Color names are not allowed.) The default is a 1-by-3 matrix of platform-dependent colors. See ColorSpec for information about RGB colors. Row 2 of the matrix is used only if the RowStriping property is on. The table background is not striped unless both RowStriping is on and the BackgroundColor color matrix has two rows.

BeingDeleted

on | {off} (read-only)

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB software sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property) It remains set to on while the delete function executes, after which the object no longer exists.

For example, some functions may not need to perform actions on objects that are being deleted, and therefore, can check the object's BeingDeleted property before acting.

BusyAction

cancel | {queue}

Callback routine interruption. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, the callback associated with the new event uses the value of BusyAction to decide whether or not to attempt to interrupt the executing callback.

- If the value is cancel, the new event is discarded and the second callback does not execute.
- If the value is queue, and the Interruptible property of the first callback is on, the second callback is added to the event queue and executes in its turn after the first callback finishes execution.

Note If the interrupting callback is DeleteFcn or CreateFcn or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. See the Interruptible property for information about controlling a callback's interruptiblity.

ButtonDownFcn

string or function handle (GUIDE sets this property)

Button-press callback routine. A callback routine that can execute when you press a mouse button while the pointer is on or near a uitable. Specifically:

- If the uitable Enable property is set to on, the ButtonDownFcn callback executes when you click the right or left mouse button in a 5-pixel border around the uitable or when you click the right mouse button on the control itself.
- If the uitable Enable property is set to inactive or off, the ButtonDownFcn executes when you click the right or left mouse button in the 5-pixel border or on the control itself.

This is useful for implementing actions to interactively modify control object properties, such as size and position, when they are clicked on (using the selectmoveresize function, for example).

Define this routine as a string that is a valid MATLAB expression or the name of an M-file. The expression executes in the MATLAB workspace.

To add a ButtonDownFcn callback in GUIDE, select View Callbacks from the Layout Editor View menu, then select ButtonDownFcn. GUIDE sets this property to the appropriate string and adds the callback to the M-file the next time you save the GUI. Alternatively, you can set this property to the string %automatic. The next time you save the GUI, GUIDE sets this property to the appropriate string and adds the callback to the M-file.

CellEditCallback

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Callback to edit user-entered data

Callback function executed when the user modifies a table cell. It can perform evaluations, validations, or other customizations. If this function is called as a function handle, uitable passes it two arguments. The first argument, source, is the handle of the uitable. The second argument, eventdata, is an event data structure that contains the fields shown in the following table. All fields in the event data structure are read only.

Event Data Structure Field	Туре	Description
Indices	1-by-2 matrix	Row index and column index of the cell the user edited.
PreviousD	alt-b y-1 matrix or cell array	Previous data for the changed cell. The default is an empty matrix, [].
EditData	String	User-entered string.

Event Data Structure Field	Туре	Description
NewData	1-by-1 matrix or cell array	Value that uitable wrote to Data. It is either the same as EditData or a converted value, for example, 2 where EditData is '2' and the cell is numeric.
		Empty if uitable detected an error in the user-entered data and did not write it to Data.
Error	String	Error that occurred when uitable tried to convert the EditData string into a value appropriate for Data. For example, uitable could not convert the EditData string consistent with the Column Format property, if any, or the data type for the changed cell.
		Empty if uitable wrote the value to Data.
		If Error is not empty, the CellEditCallback can pass the error string to the user or can attempt to manipulate the data. For example, the string 'pi' would raise an error in a numeric cell but the CellEditCallback could convert it to its numerical equivalent and store it in Data without passing the error to the user.

When a user edits a cell, uitable first attempts to store the user-entered value in Data, converting the value if necessary. It then calls the CellEditCallback and passes it the event data structure. If there is no CellEditCallback and the user-entered data results it an error, the contents of the cell reverts to its previous value and no error is displayed. **Note** In order for the CellEditCallback to be issued, after modifying a table cell the user must hit **Enter** or click somewhere else within the figure containing the table. Editing a cell's value and then clicking another figure or other window does not save the new value to the data table, and does not fire the CellEditCallback.

CellSelectionCallback

function handle, cell array containing function handle and additional arguments, or string (not recommended)

Callback that executes when cell is selected. Callback function that executes when the user highlights a cell by navigating to it or clicking it. For multiple selection, this callback executes when new cells are added to the selection. The callback includes event data, a structure with one member

Event Data Structure Field	Туре	Description
Indices		Row index and column index of the cells the user currently has selected

Once a cell selection has been made, cells within it can be removed one at a time by **Ctrl**-clicking them.

Children

matrix

The empty matrix; uitable objects have no children.

Clipping

{on} | off

This property has no effect on uitable objects.

ColumnEditable

logical 1-by-n matrix | scalar logical value |{ empty matrix ([])}

Determines if column is user-editable.

Determines if the data can be edited by the end user. Each value in the cell array corresponds to a column. False is default because the developer needs to have control over changes users potentially might make to data.

Specify elements of a logical matrix as true if the data in a column is editable by the user or false if it is not. An empty matrix indicates that no columns are editable.

Columns that contain check boxes or pop-up menus must be editable for the user to manipulate these controls. If a column that contains pop-up menus is not editable, the currently selected choice appears without displaying the pop-up control. The Elements of the ColumnEditable matrix must be in the same order as columns in the Data property. If you do not specify ColumnEditable, the default is an empty matrix ([]).

ColumnFormat

cell array of strings

Cell display formatting. Determines how the data in each column displays and is edited. Elements of the cell array must be in the same order as table columns in the Data property. If you do not want to specify a display format for a particular column, enter [] as a placeholder. If no format is specified for a column, the default display is determined by the data type of the data in the cell. Default ColumnFormat is an empty cell array ({}). In most cases, the default is similar to the command window.

Elements of the cell array must be one of the strings described in the following table.

Cell Format	Description
'char'	Displays a left-aligned string.
	To edit, the user types a string that replaces the existing string.
'logical'	Displays a check box.
	To edit, the user checks or unchecks the check box. uitable sets the corresponding Data value to true or false accordingly.
	Initially, the check box is checked if the
'numeric'	Displays a right-aligned string equivalent to the command window, for numeric data. If the cell Data value is boolean, then 1 or 0 is displayed. If the cell Data value is not numeric and not boolean, then NaN is displayed.
	To edit, the user can enter any string. This enables a user to enter a value such as 'pi' that can be converted to its numeric equivalent by a CellEditCallback. The uitable function first attempts to convert the user-entered string to a numeric value and store it in Data. It then calls the CellEditCallback. See CellEditCallback for more information.

Cell Format	Description
1-by-n cell array of strings that define a pop-up menu, e.g., {'one' 'two' 'three'}	Displays a pop-up menu. To edit, the user makes a selection from the pop-up menu. uitable sets the corresponding Data value to the selected menu item.
	The initial values for the pop-up menus in the column are the corresponding strings in Data. These initial values do not have to be items in the pop-up menu. See Example 3 on the uitable reference page.
Valid string accepted by the format function, e.g.,'short' or 'bank'	Displays the Data value using the specified format. For example, for a two-column table, set(htable,'ColumnFormat',{'short','b


In some cases, you may need to insert an appropriate column in Data. If Data is a numerical or logical matrix, you must first convert it to a cell array using the mat2cell function.

Data and ColumnFormat

When you create a table, you must specify value of Data. The Data property dictates what type of data can exist in any given cell. By default, the value of the Data also dictates the display of the cell to the end user, unless you specify a different format using the ColumnFormat property.

🔥 Fi	igure 1					×
File	Edit View	Insert T	ools Desktop	Window Hel	p	2
		Rate	Amount	Available	Fixed/Adj	
	1	6.1250	456.35	V	Fixed 💽	
	2	6.7500	510.23		Adjusta 💽	
	3	7	658.20		Fixed 💽	

ColumnFormat controls the presentation of the Data to the end user. Therefore, if you specify a ColumnFormat of char (or pick **Text** from the Table Property Editor), you are asking the table to display the Data associated with that column as a string. For example, if the Data for a particular column is numeric, and you specify the ColumnFormat as char, then the display of the numeric data will be left-aligned



If your column is editable and the user enters a number, the number will be left-aligned. However, if the user enters a text string, the table displays a **NaN**.

🔥 Fig	gu	ire 1	1										_ [IX
File	E	dit	۷	liew	Insert	T	ools	Desktop)	Window	Help			ч
					Rate		A	mount		Availabl	e	Fixed/A	١dj	
		1		6.12	50			456.35	5	▼	l I	Fixed	×.	
		2 6.7500		510.23		3			Adjusta.	. 🗵				
		3		NaN				658.20)		1	Fixed	x	
				-										

Another possible scenario is that the value Data is char and you set the ColumnFormat to be a pop-up menu. Here, if the value of the Data in the cell matches one of the pop-up menu choices you define in ColumnFormat, then the Data is shown in the cell. If it does not match, then the cell defaults to display the first option from the choices you specify in ColumnFormat. Similarly, if Data is numeric or logical with the ColumnFormat as pop-up menu, if the Data value in the cell does not match any of the choices you specify in ColumnFormat, the cell defaults to display the first option in the pop-menu choice.

This table describes how Data values correspond with your ColumnFormat when the columns are editable.

ColumnFormat Selections					
numeric	char	logical			

Uitable Properties

Data Type	numeric	Values match. MATLAB displays numbers as is.	MATLAB converts the text string entered to a double. See str2double for more information. If string cannot be converted, NaN is displayed.	Does not work: warning is thrown. Note If you have defined CellEditCallback, this warning will not be thrown
	char	MATLAB converts the entered number to a text string.	Values match. MATLAB displays the string as is.	Does not work: warning is thrown. Note If you have defined CellEditCallback, this warning will not be thrown
	logical	Does not work: warning is thrown. Note If you have defined CellEditCallback, this warning will not be thrown	If text string entered is true or false, MATLAB converts string to the corresponding logical value and displays it. For all others, it Does not work: warning is thrown.	Values match. MATLAB displays logical value as a check box as is.

	Note If you
	have defined
	CellEditCallback,
	this warning will
	not be thrown

If you get a mismatch error, you have the following options:

- Change the ColumnFormat or value of Data to match.
- Implement the CellEditCallback to handle custom data conversion.

ColumnName

1-by-*n* cell array of strings | {'numbered'} | empty matrix ([])

Column heading names. Each element of the cell array is the name of a column. Multiline column names can be expressed as a string vector separated by vertical slash (|) characters, e.g., 'Standard|Deviation'

For sequentially numbered column headings starting with 1, specify ColumnName as 'numbered'. This is the default.

To remove the column headings, specify ColumnName as the empty matrix ([]).

The number of columns in the table is the larger of ColumnName and the number of columns in the Data property matrix or cell array.

ColumnWidth

1-by-*n* cell array or 'auto'

Column widths. The width of each column in units of pixels. Column widths are always specified in pixels; they do not obey the Units property. Each column in the cell array corresponds to a column in the uitable. By default, the width of the column name, as specified in ColumnName, along with some other factors, is used to determine the width of a column. If ColumnWidth is a cell array and the width of a column is set to 'auto' or if **auto** is selected for that column in the Property Inspector GUI for columns, the column width defaults to a size determined by the table. The table decides the default size using a number of factors, including the ColumnName and the minimum column size.

To default all column widths in an existing table, use

set(uitable_handle,'ColumnWidth','auto')

To default some column widths but not others, use a cell array containing a mixture of pixel values and 'auto'. For example,

set(uitable handle, 'ColumnWidth', {64 'auto' 40 40 'auto' 72})

CreateFcn

string or function handle

Callback routine executed during object creation. The specified function executes when MATLAB creates a uitable object. MATLAB sets all property values for the uitable before executing the CreateFcn callback so these values are available to the callback. Within the function, use gcbo to get the handle of the uitable being created.

Setting this property on an existing uitable object has no effect.

You can define a default CreateFcn callback for all new uitables. This default applies unless you override it by specifying a different CreateFcn callback when you call uitable. For example, the code

set(0, 'DefaultUitableCreateFcn', 'set(gcbo,...

```
''BackGroundColor'',''blue'')')
```

creates a default CreateFcn callback that runs whenever you create a new uitable. It sets the default background color of all new uitables.

To override this default and create a uitable whose BackgroundColor is set to a different value, call uitable with code similar to

```
hpt = uitable(...,'CreateFcn','set(gcbo,...
''BackgroundColor'',''white'')')
```

Note To override a default CreateFcn callback you must provide a new callback and not just provide different values for the specified properties. This is because the CreateFcn callback runs after the property values are set, and can override property values you have set explicitly in the uitable call. In the example above, if instead of redefining the CreateFcn property for this uitable, you had explicitly set BackgroundColor to white, the default CreateFcn callback would have set BackgroundColor back to the default, i.e., blue.

Do not call copyobj or textwrap (which calls copyobj) inside a CreateFcn. The act of copying the uicontrol object fires the CreateFcn repeatedly, which raises a series of error messages after exceeding the root object's RecursionLimit property.

See "Function Handle Callbacks" for information on how to use function handles to define a callback function.

Data

matrix or cell array of numeric, logical, or character data

Data content of uitable. The matrix or cell array must be 2–dimensional. A cell array can mix data types.

Use get and set to modify Data. For example,

```
data = get(tablehandle,'Data')
data(event.indices(1),event.indices(2)) = pi();
set(tablehandle,'Data',data);
```

See CellEditCallback for information about the event data structure. See ColumnFormat for information about specifying the data display format.

The number of rows in the table is the larger of RowName and the number of rows in Data. The number of columns in the table is the larger of ColumnName and the number of columns in Data.

DeleteFcn

string or function handle

Delete uitable callback routine. A callback routine that executes when you delete the uitable object (e.g., when you issue a delete command or clear the figure containing the uitable). MATLAB executes the routine before destroying the object's properties so these values are available to the callback routine.

The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

See "Function Handle Callbacks" for information on how to use function handles to define a callback function.

Enable

{on} | inactive | off

Enable or disable the uitable. This property determines how uitables respond to mouse button clicks, including which callback routines execute.

• on – The uitable is operational (the default).

- inactive The uitable is not operational, but looks the same as when Enable is on.
- off The uitable is not operational and its image is grayed out.

When you left-click on a uitable whose Enable property is on, MATLAB performs these actions in this order:

- 1 Sets the figure's SelectionType property.
- 2 Executes the uitable's CellSelectionCallback routine (but only for table cells, not header cells). Row and column indices of the cells the user selects continuously update the Indices field in the eventdata passed to the callback.
- 3 Does not set the figure's CurrentPoint property and does not execute either the table's ButtonDownFcn or the figure's WindowButtonDownFcn callback.

When you left-click on a uitable whose Enable property is off, or when you right-click a uitable whose Enable property has any value, MATLAB performs these actions in this order:

- 1 Sets the figure's SelectionType property.
- 2 Sets the figure's CurrentPoint property.
- 3 Executes the figure's WindowButtonDownFcn callback.

Extent

position rectangle (read only)

Size of uitable rectangle. A four-element vector of the form [0,0,width,height] that contains the calculated values of the largest extent of the table based on the current Data, RowNames and ColumnNames property values. Calculation depends on column and row widths, when they are available. The calculated extent can be larger than the figure.

The first two elements are always zero. width and height are the dimensions of the rectangle. All measurements are in units specified by the Units property.

When the uitable's Units property is set to 'Normalized', its Extent is measured relative to the figure, regardless of whether the table is contained in (parented to) a uipanel or not.

You can use this property to determine proper sizing for the uitable with respect to its content. Do this by setting the width and height of the uitable Position property to the width and height of the Extent property. However, doing this can cause the table to extend beyond the right or top edge of the figure and/or its uipanel parent, if any, for tables with large extents.

FontAngle

{normal} | italic | oblique

Character slant of cell content. MATLAB uses this property to select a font from those available on your particular system. Setting this property to *italic* or *oblique* selects a slanted version of the font, when it is available on your system.

FontName

string

Font family for cell content. The name of the font in which to display cell content. To display and print properly, this must be a font that your system supports. The default font is system dependent.

To use a fixed-width font that looks good in any locale (and displays properly in Japan, where multibyte character sets are used), set FontName to the string FixedWidth (this string value is case sensitive):

```
set(uitable_handle, 'FontName', 'FixedWidth')
```

This parameter value eliminates the need to hard code the name of a fixed-width font, which may not display text properly on systems that do not use ASCII character encoding (such as in Japan). A properly written MATLAB application that needs to use a fixed-width font should set FontName to FixedWidth and rely on the root FixedWidthFontName property to be set correctly in the end user's environment.

End users can adapt a MATLAB application to different locales or personal environments by setting the root FixedWidthFontName property to the appropriate value for that locale from startup.m. Setting the root FixedWidthFontName property causes an immediate update of the display to use the new font.

FontSize

size in FontUnits

Font size for cell contents. A number specifying the size of the font in which to display cell contents, in units determined by the FontUnits property. The default point size is system dependent. If FontUnits is set to normalized, FontSize is a number between 0 and 1.

FontUnits

{points} | normalized | inches |
centimeters | pixels

Font size units for cell contents. This property determines the units used by the FontSize property. Normalized units interpret FontSize as a fraction of the height of the uitable. When you resize the uitable, MATLAB modifies the screen FontSize accordingly. pixels, inches, centimeters, and points are absolute units (1 point = $1/_{72}$ inch).

FontWeight

light | {normal} | demi | bold

Weight of cell text characters. MATLAB uses this property to select a font from those available on your particular system. Setting this property to bold causes MATLAB to use a bold version of the font, when it is available on your system.

ForegroundColor

1-by-3 matrix of RGB triples or a color name

Color of text in cells. Determines the color of the text defined for cell contents. Text in all cells share the current color. Specify as a 1-by-3 matrix of RGB triples, such as [0 0 .8] or as a color name. The default is a 1-by-3 matrix of platform-dependent colors. See ColorSpec for information about specifying RGB colors.

HandleVisibility

{on} | callback | off

Control access to object's handle. This property determines when an object's handle is visible in its parent's list of children. When a handle is not visible in its parent's list of children, it is not returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close. Neither is the handle visible in the parent figure's CurrentObject property. Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

- Handles are always visible when HandleVisibility is on.
- Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.
- Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine

invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

You can set the root ShowHiddenHandles property to on to make all handles visible, regardless of their HandleVisibility settings. This does not affect the values of the HandleVisibility properties.

HitTest

{on} | off

Selectable by mouse click. When HitTest is off, the ButtonDownFcn callback does not execute.

Interruptible

{on} | off

Callback routine interruption mode. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, that callback attempts to interrupt the first callback. The MATLAB processes the callbacks according to these factors:

- The Interruptible property of the object whose callback is executing
- Whether the executing callback contains drawnow, figure, getframe, pause, or waitfor statements
- The BusyAction property of the object whose callback is waiting to execute

If the Interruptible property of the object whose callback is executing is on (the default), the callback can be interrupted. Whenever the callback calls one of the drawnow, figure, getframe, pause, or waitfor functions, the function processes any events in the event queue, including the waiting callback, before performing its defined task. If the Interruptible property of the object whose callback is executing is off, the callback cannot be interrupted (except by certain callbacks; see the note below). The BusyAction property of the object whose callback is waiting to execute determines what happens to the callback.

Note If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. The interrupting callback starts execution at the next drawnow, figure, getframe, pause, or waitfor statement. A figure's WindowButtonDownFcn callback routine, or an object's ButtonDownFcn or Callback routine are processed according to the rules described above.

KeyPressFcn

string or function handle

Key press callback function. A callback routine invoked by a key press when the callback's uitable object has focus. Focus is denoted by a border or a dotted border, respectively, in UNIX and Microsoft Windows. If no uitable has focus, the figure's key press callback function, if any, is invoked. KeyPressFcn can be a function handle, the name of an M-file, or any legal MATLAB expression.

If the specified value is the name of an M-file, the callback routine can query the figure's CurrentCharacter property to determine what particular key was pressed and thereby limit the callback execution to specific keys.

If the specified value is a function handle, the callback routine can retrieve information about the key that was pressed from its event data structure argument.

Event Data		Examp	les:		
Structure Field	Description	a	=	Shift	Shift/a
Character	Character interpretation of the key that was pressed.	'a'	'='	1.1	'A'
Modifier	Current modifier, such as 'control', or an empty cell array if there is no modifier	{1x0 cell}	{1x0 cell}	{'shift'	'}{'shift'}
Кеу	Name of the key that was pressed.	'a'	'equal'	'shift'	'a'

The uitable KeyPressFcn callback executes for all keystrokes, including arrow keys or when a user edits cell content.

See "Function Handle Callbacks" for information on how to use function handles to define the callback function.

Parent

handle

Uitable parent. The handle of the uitable's parent object. You can move a uitable object to another figure, uipanel, or uibuttongroup by setting this property to the handle of the new parent.

Position

position rectangle

Size and location of uitable. The rectangle defined by this property specifies the size and location of the table within the parent figure window, ui, or uibuttongroup. Specify Position as a 4-element vector:

[left bottom width height]

left and bottom are the distance from the lower-left corner of the parent object to the lower-left corner of the uitable object.

width and height are the dimensions of the uitable rectangle. All measurements are in units specified by the Units property.

Note If you are specifying both Units and Position in the same call to uitable, specify Units first if you want Position to be interpreted using those units.

This object can be rearranged. The RearrangeableColumn property provides a mechanism that you can use to reorder the columns in the table. All columns are rearrangable when this property is turned on. MATLAB software sets the RearrangeableColumn property to off by default.

When this property is on, the user of a table can move any column of data (but not the row labels) at a time left or right to reorder it by clicking and dragging its header. Rearranging columns does not affect the ordering of columns in the table's Data, only the user's view of it.

RowName

1-by-n cell array of strings | { 'numbered '} | empty matrix ([])

Row heading names. Each element of the cell array is the name of a row. Row names are restricted to one line of text.

For sequentially numbered row headings starting with 1, specify RowName as 'numbered'. This is the default.

To remove the row headings, specify RowName as the empty matrix ([]).

The number of rows in the table is the larger of RowName and the number of rows in the Data property matrix or cell array.

RowStriping

{on} | off

Color striping of table rows. When RowStriping is on, the background of consecutive rows of the table display in the pair of colors that the BackgroundColor color matrix specifies. The first color matrix row applies to odd-numbered rows, and the second to even-numbered rows. If the BackgroundColor matrix has only one row, it is applied to all rows (that is, no striping occurs).

When RowStriping is off, the first color specified for BackgroundColor is applied to all rows.

Selected

on | {off}

Is object selected. When this property is on, MATLAB displays selection handles if the SelectionHighlight property is also on. You can, for example, define the ButtonDownFcn to set this property, allowing users to select the object with the mouse.

SelectionHighlight

{on} | off

Object highlight when selected. When the Selected property is on, MATLAB indicates the selected state by drawing four edge handles and four corner handles. When SelectionHighlight is off, MATLAB does not draw the handles.

Тад

string (GUIDE sets this property)

User-specified object label. The Tag property provides a means to identify graphics objects with a user-specified label. This is particularly useful when constructing interactive graphics programs that would otherwise need to define object handles as

global variables or pass them as arguments between callback routines. You can define Tag as any string.

TooltipString string

Content of tooltip for object. The TooltipString property specifies the text of the tooltip associated with the uitable. When the user moves the mouse pointer over the table and leaves it there, the tooltip is displayed.

To create a tooltip that has more than one line of text, use sprintf to generate a string containing newline (\n) characters and then set the TooltipString to that value. For example:

```
h = uitable;
s = sprintf('UITable tooltip line 1\nUITable tooltip line 2');
set(h,'TooltipString',s)
```

Туре

string (read only)

Class of graphics object. For uitable objects, Type is always the string 'uitable'.

UIContextMenu

handle

Associate a context menu with uitable. Assign this property the handle of a uicontextmenu object. MATLAB displays the context menu whenever you right-click over the uitable. Use the uicontextmenu function to create the context menu.

Units

{pixels} | normalized | inches | centimeters | points |
characters (GUIDE default: normalized)

Units of measurement. MATLAB uses these units to interpret the Extent and Position properties. All units are measured from the lower-left corner of the parent object.

- Normalized units map the lower-left corner of the parent object to (0,0) and the upper-right corner to (1.0,1.0).
- pixels, inches, centimeters, and points are absolute units (1 point = 1/72 inch).
- Character units are characters using the default system font; the width of one character is the width of the letter x, the height of one character is the distance between the baselines of two lines of text.

If you change the value of Units, it is good practice to return it to its default value after completing your computation so as not to affect other functions that assume Units is set to the default value.

UserData

matrix

User-specified data. Any data you want to associate with the uitable object. MATLAB does not use this data, but you can access it using set and get.

Visible

{on} | off

Uitable visibility. By default, all uitables are visible. When set to off, the uitable is not visible, but still exists and you can query and set its properties.

Note Setting Visible to off for uitables that are not displayed initially in the GUI, can result in faster startup time for the GUI.

uitoggletool

Purpose	Create toggle button on toolbar
Syntax	<pre>htt = uitoggletool htt = uitoggletool('PropertyName1',value1,'PropertyName2', value2,) htt = uitoggletool(ht,)</pre>
Description	htt = uitoggletool creates a toggle button on the uitoolbar at the top of the current figure window, sets all its properties to default values, and returns a handle to the tool. If no uitoolbar exists, one is created. The uitoolbar is the parent of the uitoggletool. Use the returned handle htt to set properties of the uitoggletool. The OnCallback, OffCallback and ClickedCallback use the handle as their first argument. The

and ClickedCallback use the handle as their first argument. The button has no icon, but its border highlights when you hover over it with the mouse cursor. Add an icon by setting CData for the tool. Type get(htt) to see a list of uitoggletool object properties and their current values. Type set(htt) to see a list of uitoggletool object properties you can set and legal property values.

htt =

uitoggletool('PropertyName1', value1, 'PropertyName2', value2,...)
assigns the specified property values, and assigns default values to the
remaining properties. You can change the property values at a later
time using the set function. You can specify properties as parameter
name/value pairs, cell arrays containing parameter names and values,
or structures with fields containing parameter names and values as
input arguments. For a complete list, see Uitoggletool Properties. Type
get(htt) to see a list of uipushtool object properties and their current
values. Type set(htt) to see a list of uipushtool object properties that
you can set and their legal property values.

htt = uitoggletool(ht,...) creates a button with ht as a parent. ht must be a uitoolbar handle.

Toggle tools appear in figures whose Window Style is normal or docked. They do not appear in figures with a 'modal' WindowStyle. If the WindowStyle property of a figure containing a tool bar and its toggle tool children changes to modal, the toggle tools continue to exist as Children of the tool bar. The toggle tools do not display until you change the WindowStyle to normal or docked.

Examples Create a uitoolbar object and places a uitoggletool object on it by specifying the toolbar handle as the toggle tool parent. Generate a random set of colors for the tool icon and specify a tool tip.

```
h = figure('ToolBar','none');
ht = uitoolbar(h);
a = rand(16,16,3);
htt = uitoggletool(ht,'CData',a,'TooltipString','Hello');
```



Alternatives	You can	create	toolbars	with	toggle	tools	using	GUIDE.
--------------	---------	--------	----------	------	--------	-------	-------	--------

- See Also get | set | uicontrol | uipushtool | uitoolbar
- **Tutorials** "Color Palette"
 - "Icon Editor"
- How To "Creating Toolbars"

• "Programming Toolbar Tools"

Purpose Describe toggle tool properties

Modifying Properties

You can set and query graphics object properties in two ways:

- The Property Inspector is an interactive tool that enables you to see and change object property values. The Property inspector is available from GUIDE, or use the inspect function at the command line.
- The set and get functions enable you to set and query the values of properties.

You can set default Uitoggletool properties by typing:

set(h, 'DefaultUitoggletoolPropertyName', PropertyValue...)

Where h can be the root handle (0), a figure handle, a uitoolbar handle, or a uitoggletool handle. *PropertyName* is the name of the Uitoggletool property and PropertyValue is the value you specify as the default for that property.

For more information about changing the default value of a property see "Setting Default Property Values".

Properties This section lists all properties useful to uitoggletool objects along with valid values and a descriptions of their use. Curly braces {} enclose default values.

Property	Purpose
BeingDeleted	This object is being deleted.
BusyAction	Callback routine interruption.
CData	Truecolor image displayed on the toggle tool.
ClickedCallback	Control action independent of the toggle tool position.

Property	Purpose
CreateFcn	Callback routine executed during object creation.
DeleteFcn	Callback routine executed during object deletion.
Enable	Enable or disable the uitoggletool.
HandleVisibility	Control access to object's handle.
HitTest	Whether selectable by mouse click
Interruptible	Callback routine interruption mode.
OffCallback	Control action when toggle tool is set to the off position.
OnCallback	Control action when toggle tool is set to the on position.
Parent	Handle of uitoggletool's parent toolbar.
Separator	Separator line mode.
State	Uitoggletool state.
Тад	User-specified object label.
TooltipString	Content of object's tooltip.
Туре	Object class.
UIContextMenu	Uicontextmenu object associated with the uitoggletool
UserData	User specified data.
Visible	Uitoggletool visibility.

BeingDeleted

on | {off} (read only)

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are

in the process of being deleted. MATLAB software sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property) It remains set to on while the delete function executes, after which the object no longer exists.

For example, some functions may not need to perform actions on objects that are being deleted, and therefore, can check the object's BeingDeleted property before acting.

BusyAction

cancel | {queue}

Callback routine interruption. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, the callback associated with the new event uses the value of BusyAction to decide whether or not to attempt to interrupt the executing callback.

- If the value is cancel, the event is discarded and the second callback does not execute.
- If the value is queue, and the Interruptible property of the first callback is on, the second callback is added to the event queue and executes in its turn after the first callback finishes execution.

Note If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. See theInterruptible property for information about controlling a callback's interruptibility.

CData

3-dimensional array

Truecolor image displayed on control as its icon. An n-by-m-by-3 array of RGB values that defines a truecolor image displayed on either a push button or toggle button. Each value must be between 0.0 and 1.0. If your CData array is larger than 16 in the first or second dimension, it can be clipped or result in other undesirable effects. If the array is clipped, only the center 16-by-16 part of the array is used.

ClickedCallback

string or function handle

Control action independent of the toggle tool position. A routine that executes after either the OnCallback routine or OffCallback routine runs to completion. The uitoggletool Enable property must be set to on.

CreateFcn

string or function handle

Callback routine executed during object creation. The specified function executes when MATLAB creates a uitoggletool object. MATLAB sets all property values for the uitoggletool before executing the CreateFcn callback so these values are available to the callback. Within the function, use gcbo to get the handle of the toggle tool being created.

Setting this property on an existing uitoggletool object has no effect.

You can define a default CreateFcn callback for all new uitoggletools. This default applies unless you override it by specifying a different CreateFcn callback when you call uitoggletool. For example, the statement,

```
set(0, 'DefaultUitoggletoolCreateFcn',...
'set(gcbo, ''Enable'', ''off'')'
```

creates a default CreateFcn callback that runs whenever you create a new toggle tool. It sets the toggle tool Enable property to off.

To override this default and create a toggle tool whose Enable property is set to on, you could call uitoggletool with code similar to

```
htt = uitoggletool(...,'CreateFcn',...
'set(gcbo,''Enable'',''on'')',...)
```

Note To override a default CreateFcn callback you must provide a new callback and not just provide different values for the specified properties. This is because the CreateFcn callback runs after the property values are set, and can override property values you have set explicitly in the uitoggletool call. In the example above, if instead of redefining the CreateFcn property for this toggle tool, you had explicitly set Enable to on, the default CreateFcn callback would have set CData back to off.

Do not call copyobj or textwrap (which calls copyobj) inside a CreateFcn. The act of copying the uicontrol object fires the CreateFcn repeatedly, which raises a series of error messages after exceeding the root object's RecursionLimit property.

See Function Handle Callbacks for information on how to use function handles to define a callback function.

DeleteFcn

string or function handle

Callback routine executed during object deletion. A callback routine that executes when you delete the uitoggletool object (e.g., when you call the delete function or cause the figure containing the uitoggletool to reset). MATLAB executes the routine before

destroying the object's properties so these values are available to the callback routine.

The handle of the object whose DeleteFcn is being executed is accessible only through the root CallbackObject property, which you can query using gcbo.

See Function Handle Callbacks for information on how to use function handles to define a callback function.

Enable

 $\{on\} \mid off$

Enable or disable the uitoggletool. This property controls how uitoggletools respond to mouse button clicks, including which callback routines execute.

- on The uitoggletool is operational (the default).
- off The uitoggletool is not operational and its icon (set by the Cdata property) is grayed out.

When you left-click on a uitoggletool whose Enable property is on, MATLAB performs these actions in this order:

- Executes the toggle tool OnCallback or OffCallback routine, depending on its current state, and its ClickedCallback routine.
- **2** Does *not* set the figure CurrentPoint property and does *not* execute the figure's WindowButtonDownFcn callback.
- **3** Does not set the figure SelectionType property.

When you left-click a uitoggletool whose Enable property is off, or when you right-click a uitoggletool whose Enable property has any value, no action is reported, no callback executes, and neither the SelectionType nor CurrentPoint figure properties are modified.

```
HandleVisibility
{on} | callback | off
```

Control access to object's handle. This property determines when an object's handle is visible in its parent's list of children. When a handle is not visible in its parent's list of children, it is not returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close. Neither is the handle visible in the parent figure's CurrentObject property. Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

- Handles are always visible when HandleVisibility is on.
- Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.
- Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

You can set the root ShowHiddenHandles property to on to make all handles visible, regardless of their HandleVisibility settings. This does not affect the values of the HandleVisibility properties.

HitTest

{on} | off

Selectable by mouse click. This property has no effect on uitoggletool objects.

Interruptible
 {on} | off

Callback routine interruption mode. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, that callback attempts to interrupt the first callback. MATLAB processes the callbacks according to these factors:

- The Interruptible property of the object whose callback is executing
- Whether the executing callback contains drawnow, figure, getframe, pause, or waitfor statements
- The BusyAction property of the object whose callback is waiting to execute

If the Interruptible property of the object whose callback is executing is on (the default), the callback can be interrupted. Whenever the callback calls one of the drawnow, figure, getframe, pause, or waitfor functions, the function processes any events in the event queue, including the waiting callback, before performing its defined task.

If the Interruptible property of the object whose callback is executing is off, the callback cannot be interrupted (except by certain callbacks; see the note below).

Note If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. The interrupting callback starts execution at the next drawnow, figure, getframe, pause, or waitfor statement.

OffCallback

string or function handle

Control action. A routine that executes if the uitoggletool's Enable property is set to on, and either

- The toggle tool State is set to off.
- The toggle tool is set to the off position by pressing a mouse button while the pointer is on the toggle tool itself or in a 5-pixel wide border around it.

The ClickedCallback routine, if there is one, runs after the OffCallback routine runs to completion.

OnCallback

string or function handle

Control action. A routine that executes if the uitoggletool's Enable property is set to on, and either

- The toggle tool State is set to on.
- The toggle tool is set to the on position by pressing a mouse button while the pointer is on the toggle tool itself or in a 5-pixel wide border around it.

The ClickedCallback routine, if there is one, runs after the OffCallback routine runs to completion.

Parent

handle

Uitoggletool parent. The handle of the uitoggletool's parent toolbar. You can move a uitoggletool object to another toolbar by setting this property to the handle of the new parent.

Separator

on | {off}

Separator line mode. Setting this property to on draws a dividing line to left of the uitoggletool.

State

on | {off}

Uitoggletool state. When the state is on, the toggle tool appears in the down, or pressed, position. When the state is off, it appears in the up position. Changing the state causes the appropriate OnCallback or OffCallback routine to run.

Тад

string

User-specified object identifier. The Tag property provides a means to identify graphics objects with a user-specified label. You can define Tag as any string.

With the findobj function, you can locate an object with a given Tag property value. This saves you from defining object handles as global variables. For example, this function call returns the handles of all children (of the specified toolbars) that have the Tag value 'Bold'.

```
h = findobj(uitoolbarhandles, 'Tag', 'Bold')
```

TooltipString

string

Content of tooltip for object. The TooltipString property specifies the text of the tooltip associated with the uitoggletool. When the user moves the mouse pointer over the control and leaves it there, the tooltip is displayed.

To create a tooltip that has more than one line of text, use sprintf to generate a string containing newline (\n) characters and then set the TooltipString to that value. For example:

h = uitoggletool;

s = sprintf('Toggletool tooltip line 1\nToggletool tooltip lin
set(h,'TooltipString',s)

Туре

string (read-only)

Object class. This property identifies the kind of graphics object. For uitoggletool objects, Type is always the string 'uitoggletool'.

UIContextMenu

handle

Associate a context menu with uicontrol. This property has no effect on uitoggletool objects.

UserData

array

User specified data. You can specify UserData as any array you want to associate with the uitoggletool object. The object does not use this data, but you can access it using the set and get functions.

Visible


{on} | off

Uitoggletool visibility. By default, all uitoggletools are visible. When set to off, the uitoggletool is not visible, but still exists and you can query and set its properties.

uitoolbar

Purpose	Create toolbar on figure
Syntax	<pre>ht = uitoolbar('PropertyName1',value1,'PropertyName2',value2,) ht = uitoolbar(h,)</pre>
Description	<pre>ht = uitoolbar('PropertyName1',value1,'PropertyName2',value2,) creates an empty toolbar at the top of the current figure window, and returns a handle to it. uitoolbar assigns the specified property values, and assigns default values to the remaining properties. You can change the property values at a later time using the set function.</pre>
	Type get(ht) to see a list of uitoolbar object properties and their current values. Type set(ht) to see a list of uitoolbar object properties that you can set and legal property values. See the Uitoolbar Properties reference page for more information.
	ht = uitoolbar(h,) creates a toolbar with h as a parent. h must be a figure handle.
Remarks	uitoolbar accepts property name/property value pairs, as well as structures and cell arrays of properties as input arguments.
	Uitoolbars appear in figures whose Window Style is normal or docked. They do not appear in figures whose WindowStyle is modal. If the WindowStyle property of a figure containing a uitoolbar is changed to modal, the uitoolbar still exists and is contained in the Children list of the figure, but is not displayed until the WindowStyle is changed to normal or docked.
Example	<pre>This example creates a figure with no toolbar, then adds a toolbar to it. h = figure('ToolBar', 'none') ht = uitoolbar(h)</pre>

uitoolbar



For more information on using the menus and toolbar in a MATLAB figure window, see the online MATLAB Graphics documentation.

See Also set, get, uicontrol, uipushtool, uitoggletool

Uitoolbar Properties

Purpose	Describe toolbar properties	
Modifying Properties	 You can set and query graphics object properties in two ways: The Property Inspector is an interactive tool that enables you to see and change object property values. The Property inspector is available from GUIDE, or use the inspect function at the command line. The set and get functions enable you to set and query the values of properties. You can set default Uitoolbar properties by typing: set (h, 'DefaultUitoolbarPropertyName', PropertyValue) Where h can be the root handle (0), a figure handle, or a uitoolbar handle. PropertyName is the name of the Uitoolbar property and PropertyValue is the value you specify as the default for that property. For more information about changing the default value of a property see Setting Default Property Values. This section lists all properties useful to uitoolbar objects along with valid values and a descriptions of their use. Curly braces {} enclose default values. 	
Uitoolbar Properties		
	Property	Purpose
	BeingDeleted	This object is being deleted.
	BusyAction	Callback routine interruption.
	Children	Handles of uitoolbar's children.

creation.

deletion.

Callback routine executed during object

Callback routine executed during object

CreateFcn

DeleteFcn

Property	Purpose
HandleVisibility	Control access to object's handle.
HitTest	Whether selectable by mouse click
Interruptible	Callback routine interruption mode.
Parent	Handle of uitoolbar's parent.
Тад	User-specified object identifier.
Туре	Object class.
UIContextMenu	Uicontextmenu object associated with the uitoolbar
UserData	User specified data.
Visible	Uitoolbar visibility.

BeingDeleted

on | {off} (read-only)

This object is being deleted. The BeingDeleted property provides a mechanism that you can use to determine if objects are in the process of being deleted. MATLAB software sets the BeingDeleted property to on when the object's delete function callback is called (see the DeleteFcn property) It remains set to on while the delete function executes, after which the object no longer exists.

For example, some functions may not need to perform actions on objects that are being deleted, and therefore, can check the object's BeingDeleted property before acting.

BusyAction

cancel | {queue}

Callback routine interruption. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, the callback associated with the new

event uses the value of BusyAction to decide whether or not to attempt to interrupt the executing callback.

- If the value is cancel, the event is discarded and the second callback does not execute.
- If the value is queue, and the Interruptible property of the first callback is on, the second callback is added to the event queue and executes in its turn after the first callback finishes execution.

Note If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. See the Interruptible property for information about controlling a callback's interruptibility.

Children

vector of handles

Handles of tools on the toolbar. A vector containing the handles of all children of the uitoolbar object, in the order in which they appear on the toolbar. The children objects of uitoolbars are uipushtools and uitoggletools. You can use this property to reorder the children.

CreateFcn

string or function handle

Callback routine executed during object creation. The specified function executes when MATLAB creates a uitoolbar object. MATLAB sets all property values for the uitoolbar before executing the CreateFcn callback so these values are available to the callback. Within the function, use gcbo to get the handle of the toolbar being created.

Setting this property on an existing uitoolbar object has no effect.

You can define a default CreateFcn callback for all new uitoolbars. This default applies unless you override it by specifying a different CreateFcn callback when you call uitoolbar. For example, the statement,

```
set(0,'DefaultUitoolbarCreateFcn',...
'set(gcbo,''Visibility'',''off'')')
```

creates a default CreateFcn callback that runs whenever you create a new toolbar. It sets the toolbar visibility to off.

To override this default and create a toolbar whose Visibility property is set to on, you could call uitoolbar with a call similar to

```
ht = uitoolbar(...,'CreateFcn',...
'set(gcbo,''Visibility'',''on'')',...)
```

Note To override a default CreateFcn callback you must provide a new callback and not just provide different values for the specified properties. This is because the CreateFcn callback runs after the property values are set, and can override property values you have set explicitly in the uitoolbar call. In the example above, if instead of redefining the CreateFcn property for this toolbar, you had explicitly set Visibility to on, the default CreateFcn callback would have set Visibility back to off.

Do not call copyobj or textwrap (which calls copyobj) inside a CreateFcn. The act of copying the uicontrol object fires the CreateFcn repeatedly, which raises a series of error messages after exceeding the root object's RecursionLimit property. See Function Handle Callbacks for information on how to use function handles to define a callback function.

DeleteFcn

string or function handle

Callback routine executed during object deletion. A callback function that executes when the uitoolbar object is deleted (e.g., when you call the delete function or cause the figure containing the uitoolbar to reset). MATLAB executes the routine before destroying the object's properties so these values are available to the callback routine.

Within the function, use gcbo to get the handle of the toolbar being deleted.

```
HandleVisibility
```

{on} | callback | off

Control access to object's handle. This property determines when an object's handle is visible in its parent's list of children. When a handle is not visible in its parent's list of children, it is not returned by functions that obtain handles by searching the object hierarchy or querying handle properties. This includes get, findobj, gca, gcf, gco, newplot, cla, clf, and close. Neither is the handle visible in the parent figure's CurrentObject property. Handles that are hidden are still valid. If you know an object's handle, you can set and get its properties, and pass it to any function that operates on handles.

- Handles are always visible when HandleVisibility is on.
- Setting HandleVisibility to callback causes handles to be visible from within callback routines or functions invoked by callback routines, but not from within functions invoked from the command line. This provides a means to protect GUIs from command-line users, while allowing callback routines to have complete access to object handles.

• Setting HandleVisibility to off makes handles invisible at all times. This may be necessary when a callback routine invokes a function that might potentially damage the GUI (such as evaluating a user-typed string), and so temporarily hides its own handles during the execution of that function.

You can set the root ShowHiddenHandles property to on to make all handles visible, regardless of their HandleVisibility settings. This does not affect the values of the HandleVisibility properties.

HitTest

{on} | off

Selectable by mouse click. This property has no effect on uitoolbar objects.

Interruptible

{on} | off

Callback routine interruption mode. If a callback is executing and the user triggers an event (such as a mouse click) on an object for which a callback is defined, that callback attempts to interrupt the first callback. MATLAB processes the callbacks according to these factors:

- The Interruptible property of the object whose callback is executing
- Whether the executing callback contains drawnow, figure, getframe, pause, or waitfor statements
- The BusyAction property of the object whose callback is waiting to execute

If the Interruptible property of the object whose callback is executing is on (the default), the callback can be interrupted. Whenever the callback calls one of the drawnow, figure, getframe, pause, or waitfor functions, the function processes any events in the event queue, including the waiting callback, before performing its defined task.

If the Interruptible property of the object whose callback is executing is off, the callback cannot be interrupted (except by certain callbacks; see the note below). The BusyAction property of the object whose callback is waiting to execute determines what happens to the callback.

Note If the interrupting callback is a DeleteFcn or CreateFcn callback or a figure's CloseRequest or ResizeFcn callback, it interrupts an executing callback regardless of the value of that object's Interruptible property. The interrupting callback starts execution at the next drawnow, figure, getframe, pause, or waitfor statement. A figure's WindowButtonDownFcn callback routine, or an object's ButtonDownFcn or Callback routine are processed according to the rules described above.

Parent

handle

Uitoolbar parent. The handle of the uitoolbar's parent figure. You can move a uitoolbar object to another figure by setting this property to the handle of the new parent.

Тад

string

User-specified object identifier. The Tag property provides a means to identify graphics objects with a user-specified label. You can define Tag as any string.

With the findobj function, you can locate an object with a given Tag property value. This saves you from defining object handles as global variables. For example, this function call returns the handles of all children (of the specified figures) that have the $\tt Tag$ value <code>'FormatTb'</code>.

```
h = findobj(figurehandles, 'Tag', 'FormatTb')
```

Туре

string (read-only)

Object class. This property identifies the kind of graphics object. For uitoolbar objects, Type is always the string 'uitoolbar'.

UIContextMenu

handle

Associate a context menu with uicontrol. This property has no effect on uitoolbar objects.

UserData

array

User specified data. You can specify UserData as any array you want to associate with the uitoolbar object. The object does not use this data, but you can access it using the set and get functions.

Visible

{on} | off

Uitoolbar visibility. By default, all uitoolbars are visible. When set to off, the uitoolbar is not visible, but still exists and you can query and set its properties.

uiwait

Purpose	Block execution and wait for resume			
Syntax	uiwait uiwait(h) uiwait(h,timeout)			
Description	uiwait blocks execution until uiresume is called or the current figure is deleted. This syntax is the same as uiwait(gcf).			
	uiwait(h) blocks execution until uiresume is called or the figure h is deleted.			
	uiwait(h,timeout) blocks execution until uiresume is called, the figure h is deleted, or timeout seconds elapse. The minimum value of timeout is 1. If uiwait receives a smaller value, it issues a warning and uses a 1 second timeout.			
Remarks	The uiwait and uiresume functions block and resume MATLAB and Simulink program execution. uiwait also blocks the execution of Simulink models. The functions pause (with no argument) and waitfor also block execution in this manner.uiwait is a convenient way to use the waitfor command. You typically use it in conjunction with a dialog box. It provides a way to block the execution of the M-file that created the dialog, until the user responds to the dialog box. When used in conjunction with a modal dialog, uiwait can block the execution of the M-file <i>and</i> restrict user interaction to the dialog only.			
Example	<pre>This example creates a GUI with a Continue push button. The example calls uiwait to block MATLAB execution until uiresume is called. This happens when the user clicks the Continue push button because the push button's Callback callback, which responds to the click, calls uiresume. f = figure; h = uicontrol('Position',[20 20 200 40],'String','Continue',</pre>			

```
uiwait(gcf);
disp('This will print after you click Continue');
close(f);
```

gcbf is the handle of the figure that contains the object whose callback is executing.

"Using a Modal Dialog Box to Confirm an Operation" is a more complex example for a GUIDE GUI. See "Icon Editor" for an example for a programmatically created GUI.

See Also dialog, figure, uicontrol, uimenu, uiresume, waitfor

undocheckout

Purpose	Undo previous checkout from source control system (UNIX platforms)			
GUI Alternatives	As an alternative to the undocheckout function, select Source Control > Undo Checkout in the File menu of the Editor, Simulink software, or Stateflow software, or in the context menu of the Current Folder browser.			
Syntax	undocheckout('filename') undocheckout({'filename1','filename2',,'filenamen'})			
Description	undocheckout('filename') makes the file filename available for checkout, where filename does not reflect any of the changes you made after you last checked it out. Use the full path for filename and include the file extension.			
	undocheckout({'filename1','filename2',,'filenamen'}) makes filename1 through filenamen available for checkout, where the files do not reflect any of the changes you made after you last checked them out. Use the full paths for the file names and include the file extensions.			
Examples	Undo the checkouts of /myserver/myfiles/clock.m and /myserver/myfiles/calendar.m from the source control system:			
	undocheckout({'/myserver/myfiles/clock.m', '/myserver/myfiles/calendar.m'})			
See Also	checkin, checkout			
	• For Microsoft Windows platforms, use verctrl.			
	 For more information, see "Undoing the Checkout on UNIX Platforms". 			

Purpose	Convert Unicode characters to numeric bytes				
Syntax	bytes = unicode2native(unicodestr) bytes = unicode2native(unicodestr, encoding)				
Description	<pre>bytes = unicode2native(unicodestr) takes a char vector of Unicode characters, unicodestr, converts it to the MATLAB default character encoding scheme, and returns the bytes as a uint8 vector, bytes. Output vector bytes has the same general array shape as the unicodestr input. You can save the output of unicode2native to a file using the fwrite function.</pre>				
	<pre>bytes = unicode2native(unicodestr, encoding) converts the Unicode characters to the character encoding scheme specified by the string encoding. encoding must be the empty string ('') or a name or alias for an encoding scheme. Some examples are 'UTF-8', 'latin1', 'US-ASCII', and 'Shift_JIS'. For common names and aliases, see the Web site http://www.iana.org/assignments/character-sets. If encoding is unspecified or is the empty string (''), the MATLAB default encoding scheme is used.</pre>				
Examples	<pre>This example begins with two strings containing Unicode characters. It assumes that string str1 contains text in a Western European language and string str2 contains Japanese text. The example writes both strings into the same file, using the ISO-8859-1 character encoding scheme for the first string and the Shift-JIS encoding scheme for the second string. The example uses unicode2native to convert the two strings to the appropriate encoding schemes. fid = fopen('mixed.txt', 'w'); bytes1 = unicode2native(str1, 'ISO-8859-1'); fwrite(fid, bytes1, 'uint8'); bytes2 = unicode2native(str2, 'Shift_JIS'); fwrite(fid, bytes2, 'uint8');</pre>				
See Ales	<pre>fclose(fid);</pre>				
See Also	native2unicode				

union

Purpose	Find set union of two vectors					
Syntax	c = union(A, B) c = union(A, B, 'rows') [c, ia, ib] = union()					
Description	c = union(A, B) returns the combined values from A and B but with no repetitions. In set theoretic terms, $c = A \cup B$. Inputs A and B can be numeric or character vectors or cell arrays of strings. The resulting vector is sorted in ascending order.					
	c = union(A, B, 'rows') when A and B are matrices with the same number of columns returns the combined rows from A and B with no repetitions. MATLAB ignores the rows flag for all cell arrays.					
	[c, ia, ib] = union() also returns index vectors ia and ib such that $c = a(ia) \cup b(ib)$, or for row combinations, $c = a(ia,:) \cup b(ib,:)$. If a value appears in both a and b, union indexes its occurrence in b. If a value appears more than once in b or in a (but not in b), union indexes the last occurrence of the value.					
Remarks	Because NaN is considered to be not equal to itself, every occurrence of NaN in A or B is also included in the result c.					
Examples	a = [-1 0 2 4 6]; b = [-1 0 1 3]; [c, ia, ib] = union(a, b); c =					
	-1 0 1 2 3 4 6					
	ia =					
	3 4 5					
	ib =					

1 2 3 4

See Also intersect, setdiff, setxor, unique, ismember, issorted

unique

Purpose	Find unique elements of vector					
Syntax	<pre>b = unique(A) b = unique(A, 'rows') [b, m, n] = unique() [b, m, n] = unique(, occurrence)</pre>					
Description	 b = unique(A) returns the same values as in A but with no repetitions. A can be a numeric or character array or a cell array of strings. If A is a vector or an array, b is a vector of unique values from A. If A is a cell array of strings, b is a cell vector of unique strings from A. The resulting vector b is sorted in ascending order and its elements are of the same class as A. 					
	<pre>b = unique(A, 'rows') returns the unique rows of A.</pre>					
	[b, m, n] = unique() also returns index vectors m and n such that $b = A(m)$ and $A = b(n)$. Each element of m is the greatest subscript such that $b = A(m)$. For row combinations, $b = A(m,:)$ and $A = b(n,:)$.					
	<pre>[b, m, n] = unique(, occurrence), where occurrence can be</pre>					
	• 'first', which returns the vector m to index the first occurrence of each unique value in A, or					
	 'last', which returns the vector m to index the last occurrence. If you do not specify occurrence, it defaults to 'last'. 					
	You can specify 'rows' in the same command as 'first' or 'last'. The order of appearance in the argument list is not important.					
Examples	A = [1 1 5 6 2 3 3 9 8 6 2 4] A = 1 1 5 6 2 3 3 9 8 6 2 4					

Get a sorted vector of unique elements of A. Also get indices of the first elements in A that make up vector b, and the first elements in b that make up vector A:

[b1, m1, n1] = unique(A, 'first') b1 = З m1 = 6 12 n1 = Verify that b1 = A(m1) and A = b1(n1): all(b1 == A(m1)) & all(A == b1(n1))ans =

Get a sorted vector of unique elements of A. Also get indices of the last elements in A that make up vector b, and the last elements in b that make up vector A:

[b2, m2, n2] = unique(A, 'last') b2 = m2 = n2 = Verify that b2 = A(m2) and A = b2(n2):

```
all(b2 == A(m2)) && all(A == b2(n2))
ans =
1
```

Because NaNs are not equal to each other, unique treats them as unique elements.

unique([1 1 NaN NaN]) ans = 1 NaN NaN

See Also intersect, ismember, sort, issorted, setdiff, setxor, union

Purpose	Execute UNIX command and return result			
Syntax	unix command status = unix('command') [status, result] = unix('command') [status,result] = unix('command',' -echo ')			

Description	unix command calls upon the UNIX ¹⁹ operating system to execute the given command. The command executes in a UNIX shell, not in the shell that you used to launch MATLAB.					
	<pre>status = unix('command') returns completion status to the status variable.</pre>					
	[status, result] = unix('command') returns the standard output to the result variable, in addition to completion status.					
	[status,result] = unix('command','-echo') displays the results in the Command Window as it executes, and assigns the results to result.					
	This function is interchangeable with the system and dos functions. They all have the same effect.					
Examples	List all users that are currently logged in.					
	[s,w] = unix('who');					
	MATLAB returns 0 (success) in ${\bf s}$ and a string containing the list of users in w.					
	Try to execute a string that isn't a UNIX command.					
	[s,w] = unix('why') s = 1					
	w =					
	why: Command not found.					
	MATLAB returns a nonzero value in s to indicate failure, and returns an error message in w because why is not a UNIX command.					

Algorithm The MATLAB software uses a shell program to execute the given command. It determines which shell program to use by checking

19. UNIX is a registered trademark of The Open Group in the United States and other countries.

environment variables on your system. MATLAB first checks the MATLAB_SHELL variable, and if either empty or not defined, then checks SHELL. If SHELL is also empty or not defined, MATLAB uses /bin/sh.


See Also dos | ! (exclamation point) | perl | system

Tutorials • "Running External Programs"

unloadlibrary

Purpose	Unload shared library from memory			
Syntax	unloadlibrary('libname') unloadlibrary libname			
Description	unloadlibrary('libname') unloads the shared library libname from memory. If you need to use functions in this library, you must reload the library using the loadlibrary function.			
	unloadlibrary libname is the command format for this function.			
	If you used an alias when initially loading the library, then you must use that alias for the libname argument.			
Examples	Load the MATLAB sample shared library, shrlibsample. Call on its functions, and then unload the library:			
	addpath([matlabroot '\extern\examples\shrlib']) loadlibrary shrlibsample shrlibsample.h			
	s.p1 = 476; s.p2 = -299; s.p3 = 1000; calllib('shrlibsample', 'addStructFields', s) ans = 1177			
	unloadlibrary shrlibsample			
See Also	loadlibrary, libisloaded			

Purpose	Convert edge matrix to coordinate and Laplacian matrices			
Syntax	[L,XY] = unmesh(E)			
Description	[L,XY] = unmesh(E) returns the Laplacian matrix L and mesh vertex coordinate matrix XY for the M-by-4 edge matrix E. Each row of the edge matrix must contain the coordinates $[x1 y1 x2 y2]$ of the edge endpoints.			
Input Arguments	E	M-by-4 edge matrix E.		
Output Arguments	L XY	Laplacian matrix representation of the graph. Mesh vertex coordinate matrix.		
Examples	Take a simple example of a square with vertices at $(1,1)$, $(1,-1)$, $(-1,-1)$, and $(-1,1)$, where the connections between vertices are the four perpendicular edges of the square plus one diagonal connection between $(-1, -1)$ and $(1,1)$.			



The edge matrix E for this graph is:

E=[1 1 1 -1;	%	edge	from	1	to	2
1 -1 -1 -1;	%	edge	from	2	to	3
-1 -1 -1 1;	%	edge	from	3	to	4
-1 -1 1 1;	%	edge	from	4	to	1
-1 1 1 1]	%	edge	from	3	to	1

Use unmesh to create the output matrices,

```
[A,XY]=unmesh(E);
4 vertices:
4/4
```

The Laplacian matrix is defined as

$$L_{ij} = \begin{cases} \deg(v_i) & \text{ if } i = j \\ -1 & \text{ if } i \neq j \text{ and } v_i \text{ is adjacent to } v_j \\ 0 & \text{ otherwise} \end{cases}$$

unmesh returns the Laplacian matrix ${\sf L}$ in sparse notation.

L

L =

(1,1)	3
(2,1)	- 1
(3,1)	- 1
(4,1)	- 1
(1,2)	- 1
(2,2)	2
(4,2)	- 1
(1,3)	- 1
(3,3)	2
(4,3)	- 1
(1,4)	- 1
(2,4)	- 1
(3,4)	- 1

To see ${\tt L}$ in regular matrix notation, use the full command.

- 1

- 1

- 1

3

full(L) ans = 3 -1 -1 -1 2 0 -1 0 2 -1 -1 -1

The mesh coordinate matrix XY returns the coordinates of the corners of the square.

XY		
XY	=	
	- 1	- 1
	- 1	1
	1	- 1
	1	1

See Also

gplot treeplot

Purpose Piecewise polynomial details

Syntax [breaks,coefs,1,k,d] = unmkpp(pp)

Description [breaks,coefs,l,k,d] = unmkpp(pp) extracts, from the piecewise polynomial pp, its breaks breaks, coefficients coefs, number of pieces l, order k, and dimension d of its target. Create pp using spline or the spline utility mkpp.

Examples This example creates a description of the quadratic polynomial

$$\frac{-x^2}{4} + x$$

as a piecewise polynomial ${\sf pp},$ then extracts the details of that description.

```
pp = mkpp([-8 -4],[-1/4 1 0]);
[breaks,coefs,l,k,d] = unmkpp(pp)
breaks =
      -8 -4
coefs =
      -0.2500 1.0000 0
l =
      1
k =
      3
d =
      1
```

See Also mkpp, ppval, spline

unregisterallevents

Purpose	Unregister all event handlers associated with COM object events at run time	
Syntax	h.unregisterallevents unregisterallevents(h)	
Description	h.unregisterallevents unregisters all events previously registered with COM object h. After calling unregisterallevents, the object no longer responds to any events until you register them again using the registerevent function.	
	unregisterallevents(h) is an alternate syntax.	
	COM functions are available on Microsoft Windows systems only.	
Examples	Register and unregister events for an instance of the mwsamp control, using the eventlisteners function to see the event handler associated with each event:	
	1 Register three events and their respective handler routines.	
	<pre>f = figure ('position', [100 200 200 200]); h = actxcontrol('mwsamp.mwsampctrl.2', [0 0 200 200], f, {'Click' 'myclick'; 'DblClick' 'my2click'; 'MouseDown' 'mymoused'}); h.eventlisteners</pre>	
	MATLAB displays:	
	<pre>ans = 'click' 'myclick' 'dblclick' 'my2click' 'mousedown' 'mymoused'</pre>	
	2 Unregister all events simultaneously with unregisterallevents.	

2 Unregister all events simultaneously with unregisterallevents. eventlisteners returns an empty cell array, indicating that there are no longer any events registered with the control:

```
h.unregisterallevents;
h.eventlisteners
MATLAB displays:
ans =
{}
See Also
events (COM) | eventlisteners | registerevent | unregisterevent
| isevent
```

unregisterevent

Purpose	Unregister event handler associated with COM object event at run time
Syntax	h.unregisterevent(eventhandler) unregisterevent(h, eventhandler)
Description	h.unregisterevent(eventhandler) unregisters specific event handler routines from their corresponding events. Once you unregister an event, the object no longer responds to the event.
	unregisterevent(h, eventhandler) is an alternate syntax.
	You can unregister events at any time after creating a control. The eventhandler argument, which is a cell array, specifies both events and event handlers.
	h.unregisterevent({'event_name',@event_handler});
	Specify events in the eventhandler argument using the names of the events. Strings used in the eventhandler argument are not case sensitive. unregisterevent does not accept numeric event identifiers.
	COM functions are available on Microsoft Windows systems only.
Examples	Unregister events for a control:
	1 Create an mwsamp control and register all events with the same handler routine, sampev. Use eventlisteners to see the event handler used by each event. In this case, each event, when fired, calls sampev.m:
	<pre>f = figure ('position', [100 200 200 200]); h = actxcontrol('mwsamp.mwsampctrl.2', [0 0 200 200], f, 'sampev'); h.eventlisteners</pre>
	MATLAB displays:

```
ans =

'Click' 'sampev'

'DblClick' 'sampev'

'MouseDown' 'sampev'

'Event Args' 'sampev'
```

2 Unregister just the dblclick event. Now, when you list the registered events using eventlisteners, dblclick is no longer registered and the control does not respond when you double-click the mouse over it:

h.unregisterevent({'dblclick' 'sampev'}); h.eventlisteners

MATLAB displays:

ans = 'Click' 'sampev' 'MouseDown' 'sampev' 'Event_Args' 'sampev'

3 Now, register the click and dblclick events with a different event handler for myclick and my2click, respectively:

```
h.unregisterallevents;
h.registerevent({'click' 'myclick'; ...
    'dblclick' 'my2click'});
h.eventlisteners
```

MATLAB displays:

ans = 'click' 'myclick' 'dblclick' 'my2click'

4 Unregister these same events by specifying event names and their handler routines in a cell array. eventlisteners now returns an

empty cell array, meaning that no events are registered for the mwsamp control:

```
h.unregisterevent({'click' 'myclick'; ...
    'dblclick' 'my2click'});
h.eventlisteners
```

MATLAB displays:

ans = {}

Unregister Microsoft Excel workbook events:

1 Create a Workbook object and register two events with the event handler routines, EvtActivateHndlr and EvtDeactivateHndlr:

```
myApp = actxserver('Excel.Application');
wbs = myApp.Workbooks;
wb = wbs.Add;wb.registerevent({'Activate' 'EvtActivateHndlr'; ...
    'Deactivate' 'EvtDeactivateHndlr'})
wb.eventlisteners
```

MATLAB shows the events with the corresponding event handlers.

ans =
 'Activate' 'EvtActivateHndlr'
 'Deactivate' 'EvtDeactivateHndlr'

2 Next, unregister the Deactivate event handler:

```
wb.unregisterevent({'Deactivate' 'EvtDeactivateHndlr'})
wb.eventlisteners
```

MATLAB shows the remaining registered event (Activate) with its corresponding event handler.

	ans = 'Activate'	'EvtActivateHndlr'
See Also	events (COM) eventlisteners registerevent unregisterallevents isevent	
How To	• "Writing Event Handl	ers"

untar

Purpose	Extract contents of tar file
Syntax	untar(tarfilename) untar(tarfilename,outputdir) untar(url,) filenames = untar()
Description	untar(tarfilename) extracts the archived contents of tarfilename into the current directory and sets the files' attributes. It overwrites any existing files with the same names as those in the archive if the existing files' attributes and ownerships permit it. For example, if you rerun untar on the same tarfilename, MATLAB software does not overwrite files with a read-only attribute; instead, untar displays a warning for such files. On Microsoft Windows platforms, the hidden, system, and archive attributes are not set.
	tarfilename is a string specifying the name of the tar file. tarfilename is gunzipped to a temporary directory and deleted if its extension ends in .tgz or .gz. If an extension is omitted, untar searches for tarfilename appended with .tgz, .tar.gz, or .tar. tarfilename can include the directory name; otherwise, the file must be in the current directory or in a directory on the MATLAB path.
	untar(tarfilename,outputdir) uncompresses the archive tarfilename into the directory outputdir. If outputdir does not exist, MATLAB creates it.
	untar(url,) extracts the tar archive from an Internet URL. The URL must include the protocol type (for example, 'http://' or 'ftp://'). MATLAB downloads the URL is to a temporary directory, and then deletes it.
	filenames = untar() extracts the tar archive and returns the names of the extracted files in the string cell array filenames. If outputdir specifies a relative path, filenames contains the relative path. If outputdir specifies an absolute path, filenames contains the absolute path.

Examples Using tar and untar to Copy Files

Copy all .m files in the current directory to the directory backup.

```
tar('mymfiles.tar.gz','*.m');
untar('mymfiles','backup');
```

Using untar with URL

Run untar to list Cleve Moler's "Numerical Computing with MATLAB" examples to the output directory ncm.

url ='http://www.mathworks.com/moler/ncm.tar.gz'; ncmFiles = untar(url,'ncm')

See Also gzip, gunzip, tar, unzip, zip

unwrap


Purpose	Correct phase angles to produce smoother phase plots
Syntax	<pre>Q = unwrap(P) Q = unwrap(P,tol) Q = unwrap(P,[],dim) Q = unwrap(P,tol,dim)</pre>
Description	Q = unwrap(P) corrects the radian phase angles in a vector P by adding multiples of $\pm 2\pi$ when absolute jumps between consecutive elements of P are greater than or equal to the default jump tolerance of π radians. If P is a matrix, unwrap operates columnwise. If P is a multidimensional array, unwrap operates on the first nonsingleton dimension. Q = unwrap(P,tol) uses a jump tolerance tol instead of the default value, π .
	Q = unwrap(P,[],dim) unwraps along dim using the default tolerance.
	Q = unwrap(P,tol,dim) uses a jump tolerance of tol.
	Note A jump tolerance less than π has the same effect as a tolerance of π . For a tolerance less than π , if a jump is greater than the tolerance but less than π , adding $\pm 2\pi$ would result in a jump larger than the existing one, so unwrap chooses the current point. If you want to eliminate jumps that are less than π , try using a finer grid in the domain.
F	

Examples Example 1

The following phase data comes from the frequency response of a third-order transfer function. The phase curve jumps 3.5873 radians between w = 3.0 and w = 3.5, from -1.8621 to 1.7252.


```
w = [0:.2:3,3.5:1:10];
p = [ 0
        -1.5728
        -1.5747
        -1.5772
```

-1.5790 -1.5816 -1.5852 -1.5877 -1.5922 -1.5976 -1.6044 -1.6129 -1.6269 -1.6512 -1.6998 -1.8621 1.7252 1.6124 1.5930 1.5916 1.5708 1.5708 1.5708]; semilogx(w,p,'b*-'), hold



Using unwrap to correct the phase angle, the resulting jump is 2.6959, which is less than the default jump tolerance π . This figure plots the new curve over the original curve.

semilogx(w,unwrap(p),'r*-')



Example 2

Array P features smoothly increasing phase angles except for discontinuities at elements (3,1) and (1,2).

P = [0	7.0686	1.5708	2.3562
0.1963	0.9817	1.7671	2.5525
6.6759	1.1781	1.9635	2.7489
0.5890	1.3744	2.1598	2.9452]

The function Q = unwrap(P) eliminates these discontinuities.

0	7.0686	1.5708	2.3562
0.1963	7.2649	1.7671	2.5525
0.3927	7.4613	1.9635	2.7489
0.5890	7.6576	2.1598	2.9452

See Also abs, angle

Purpose	Extract contents of zip file
Syntax	<pre>unzip(zipfilename) unzip(zipfilename, outputdir) unzip(url,) filenames = unzip()</pre>
Description	unzip(<i>zipfilename</i>) extracts the archived contents of <i>zipfilename</i> into the current folder, preserving the files' attributes and timestamps. If <i>zipfilename</i> does not include the full path, unzip searches for the file in the current folder and along the MATLAB path. If you do not specify the file extension, unzip appends .zip.
	unzip(<i>zipfilename</i> , <i>outputdir</i>) extracts the contents of <i>zipfilename</i> into the folder <i>outputdir</i> .
	unzip(<i>url</i> ,) extracts the zipped contents from an Internet URL. The URL must include the protocol type (for example, http://). The unzip function downloads the URL to the temporary folder on your system, and deletes the URL on cleanup.
	<pre>filenames = unzip()returns the names of the extracted files in the string cell array filenames. If outputdir specifies a relative path, filenames contains the relative path. If outputdir specifies an absolute path, filenames contains the absolute path.</pre>
Tips	• unzip does not support password-protected or encrypted zip archives.
	• If any files in the target folder have the same name as files in the zip file, and you have write permission to the files, unzip overwrites the existing files with the archived versions. If you do not have write permission, unzip issues a warning.
	• Extract files that contain non-7-bit ASCII characters on a machine that has the appropriate language/encoding settings.
Examples	Copy the demo MAT-files to the folder archive:
	% Zip the demo MAT-files to demos.zip

```
zip('demos.zip','*.mat',...
fullfile(matlabroot,'toolbox','matlab','demos'))
% Unzip demos.zip to the folder 'archive'
unzip('demos','archive')
```

Download Cleve Moler's "Numerical Computing with MATLAB" examples to the output folder ncm:

url ='http://www.mathworks.com/moler/ncm.zip'; ncmFiles = unzip(url,'ncm')

See Also fileattrib | gzip | gunzip | tar | untar | zip

Purpose	Convert string to uppercase	
Syntax	t = upper('str') B = upper(A)	
Description	<pre>t = upper('str') converts any lowercase characters in the string str to the corresponding uppercase characters and leaves all other characters unchanged.</pre>	
	B = upper(A) when A is a cell array of strings, returns a cell array the same size as A containing the result of applying upper to each string within A.	
Examples	upper('attention!') is ATTENTION!.	
Remarks	Character sets supported:	
	• PC: Windows Latin-1	
	• Other: ISO Latin-1 (ISO 8859-1)	
See Also	lower	

urlread

Purpose	Download content at URL into MATLAB string
Syntax	<pre>str = urlread(URL) str = urlread(URL, method, params) [str, status] = urlread()</pre>
Description	<pre>str = urlread(URL) reads Web content at the specified URL into the string str. If the server returns binary data, str is unreadable.</pre>
	<pre>str = urlread(URL, method, params) uses a method of 'get' or 'post', and passes information in params to the server. params is a cell array of parameter name/value pairs.</pre>
	[<i>str</i> , <i>status</i>] = urlread() returns a <i>status</i> of 1 when the operation is successful. Otherwise, <i>status</i> is 0.
	To save Web content to a file instead of a string, use urlwrite.
Examples	Download the page on the MATLAB Central File Exchange that lists submissions related to urlread, found at http://www.mathworks.com/matlabcentral/fileexchange/?term=urlread.
	<pre>samples = urlread(</pre>
Alternatives	urlread and urlwrite can download content from FTP sites. Alternatively, use the ftp function to connect to an FTP server and the mget function to download a file.
See Also	urlwrite ftp web
How To	"Specifying Proxy Server Settings"

Purpose	Download content at URL and save to file
Syntax	<pre>urlwrite(URL, filename) urlwrite(URL, filename, method, params) f = urlwrite() [f, status] = urlwrite()</pre>
Description	urlwrite(URL, filename) reads Web content at the specified URL and saves it to filename. If you do not specify the path for filename, urlwrite saves the file in the MATLAB current folder.
	urlwrite(URL, filename, method, params) uses a method of 'get' or 'post', and passes information in params to the server. params is a cell array of parameter name/value pairs.
	f = urlwrite() assigns filename to f.
	<pre>[f, status] = urlwrite() returns a status of 1 when the operation is successful. Otherwise, status is 0.</pre>
Examples	Download the page on the MATLAB Central File Exchange that lists submissions related to urlwrite, found at http://www.mathworks.com/matlabcentral/fileexchange/?term=urlwrite. Save the results to samples.html in the current directory.
	urlwrite('http://www.mathworks.com/matlabcentral/fileexchange', 'samples.html', 'get', {'term','urlwrite'});
	View the file in the Help browser:
	open('samples.html')
Alternatives	urlread and urlwrite can download content from FTP sites. Alternatively, use the ftp function to connect to an FTP server and the mget function to download a file.

urlwrite

See Also	urlread ftp web
How To	"Specifying Proxy Server Settings"

Purpose	Determine whether Sun Java feature is supported in MATLAB software
Syntax	usejava(feature)

Description usejava(feature) returns 1 if the specified feature is supported and 0 otherwise.

The following table shows the valid feature arguments.

Feature	Description
'awt'	Java GUI components in the Abstract Window Toolkit components are available.
'desktop'	The MATLAB interactive desktop is running.
'jvm'	The Java Virtual Machine software(JVM) is running.
'swing'	Swing components (Java lightweight GUI components in the Java Foundation Classes) are available.

Examples

The following conditional code ensures that the AWT GUI components are available before the script attempts to display a Java Frame.

```
if usejava('awt')
    myFrame = java.awt.Frame;
else
    disp('Unable to open a Java Frame');
end
```

The next example is part of a script that includes Java code. It fails gracefully when run in a MATLAB session that does not have access to JVM software.

```
if ~usejava('jvm')
    error([mfilename ' requires Java to run.']);
end
```

See Also

javachk

Purpose	View or change user portion of search path
Syntax	userpath userpath('newpath') userpath(' reset ') userpath(' clear ')
Description	userpath returns a string specifying the user portion of the search path. The user portion of the search path is the first folder on the search path, above the folders supplied by The MathWorks. The default folder is My Documents/MATLAB on Microsoft Windows platforms, and Documents/MATLAB on Microsoft Windows Vista [™] platforms.

On Apple Macintosh and UNIX²⁰ platforms, the default value is userhome/Documents/MATLAB. You can define the userpath folder to also be the MATLAB startup folder. On Windows platforms, userpath is the startup folder, unless the startup folder is otherwise specified, such as by the MATLAB shortcut properties **Start in** field. On UNIX and Macintosh platforms, the startup folder is userpath if the value of the environment variable MATLAB_USE_USERPATH is set to 1 prior to startup and if the startup folder is not otherwise specified, such as via a startup.m file. On Macintosh and UNIX platforms, you can automatically add additional subfolders to the top of the search path upon startup by specifying the path for the subfolders via the MATLABPATH environment variable.

userpath('newpath') sets the *userpath* value to newpath. The newpath folder appears at the top of the search path immediately and at startup in future sessions. MATLAB removes the folder previously specified by *userpath* from the search path. newpath must be an absolute path. userpath('newpath') does not work when the -nojvm startup option is used. Upon the next startup, newpath, can become the current folder, as described in the syntax for userpath with no arguments.

userpath('reset') sets the userpath value to the default for that platform, creating the Documents/MATLAB (or My Documents/MATLAB) folder, if it does not exist. MATLAB immediately adds the default folder to the top of the search path, and also adds it to the search path at startup in future sessions. It can become the startup folder as described for the userpath syntax with no arguments. MATLAB removes the folder previously specified by userpath from the search path. userpath('reset') does not work when the -nojvm startup option is used.

userpath('clear') clears the value for *userpath*. MATLAB removes the folder previously specified by *userpath* from the search path. This does not work when the -nojvm startup option is used. You

20. UNIX is a registered trademark of The Open Group in the United States and other countries.

can otherwise specify the startup folder—see "Startup Folder for the MATLAB Program".

Examples • "Viewing *userpath*" on page 2-4333

- "Setting a New Value for *userpath*" on page 2-4334
- "Clearing the Value for *userpath*, and Specifying a New Startup Folder on Windows Platforms" on page 2-4335
- "Removing *userpath* from the Search Path; Resets the Startup Folder" on page 2-4336
- "Assigning *userpath* as the Startup Folder on a UNIX or Macintosh Platform" on page 2-4338
- "Adding Folders to the Search Path Upon Startup on a UNIX or Macintosh Platform" on page 2-4339

Viewing userpath

This example assumes *userpath* is set to the default value on the Windows XP platform, My Documents\MATLAB. Start MATLAB and display the current folder:

cd

MATLAB returns:

H:\My Documents\MATLAB

where H is the drive at which My Documents is located for this example. Confirm the current folder is the *userpath*:

userpath

MATLAB returns:

H:\My Documents\MATLAB;

Display the search path:

path

MATLAB returns the search path. The *userpath* portion is at the top:

MATLABPATH

```
H:\My Documents\MATLAB
C:\Program Files\MATLAB\R2009a\toolbox\matlab\general
C:\Program Files\MATLAB\R2009a\toolbox\matlab\ops
```

Setting a New Value for userpath

This example assumes *userpath* is set to the default value on the Windows XP platform, My Documents\MATLAB. Change the value from the default for *userpath* to C:\Research_Project:

```
userpath('C:\Research_Project')
```

View the effect of the change on the search path:

path

MATLAB displays the search path, with the new value for *userpath* portion at the top:

MATLABPATH

```
C:\Research_Project
C:\Program Files\MATLAB\R2009a\toolbox\matlab\general
C:\Program Files\MATLAB\R2009a\toolbox\matlab\ops
...
```

Note that MATLAB automatically removed the previous value of *userpath*, H:\My Documents\MATLAB, from the search path when you assigned a new value to *userpath*. The next time you start MATLAB, the current folder will be C:\Research_Project on Windows platforms.

Clearing the Value for *userpath,* and Specifying a New Startup Folder on Windows Platforms

userpath is set to the default value and you do not want any folders to be added to the search path upon startup. Confirm the default is currently set:

userpath

MATLAB returns:

H:\My Documents\MATLAB

Verify that the *userpath* folder is at the top of the search path:

path

MATLAB returns:

MATLABPATH

```
H:\My Documents\MATLAB
C:\Program Files\MATLAB\R2009a\toolbox\matlab\general
C:\Program Files\MATLAB\R2009a\toolbox\matlab\ops
...
```

Clear the value:

userpath('clear')

Verify the result:

userpath

MATLAB returns:

ans =

Confirm the *userpath* folder was removed from the search path:

path

MATLAB returns

MATLABPATH

```
C:\Program Files\MATLAB\R2009a\toolbox\matlab\general
C:\Program Files\MATLAB\R2009a\toolbox\matlab\ops
...
```

After clearing the *userpath* value, unless you otherwise specify the startup folder, the startup folder will be the desktop on Windows platforms. There are a number of ways to specify the startup folder. For example, right-click the Windows shortcut icon for MATLAB and select **Properties** from the context menu. In the Properties dialog box **Shortcut** tab, enter the full path to the new startup folder in the **Start in** field, for example, I\:my_matlab_files\my_files. The next time you start MATLAB, the current folder will be I\:my_matlab_files\my_files, but that folder will *not* be on the search path. Note that you do not have to clear *userpath* to specify a different startup folder; when you otherwise specify a startup folder, the *userpath* folder is added to the search path upon startup, but is not the startup folder.

Removing *userpath* from the Search Path; Resets the Startup Folder

In this example, *userpath* is set to the default value and you remove the *userpath* folder from the search path, then save the changes. This has the same effect as clearing the value for *userpath*. Confirm the default is currently set:

userpath

MATLAB returns:

H:\My Documents\MATLAB

See the *userpath* folder at the top of the search path:

path

MATLAB returns:

MATLABPATH

H:\My Documents\MATLAB
C:\Program Files\MATLAB\R2009a\toolbox\matlab\general
C:\Program Files\MATLAB\R2009a\toolbox\matlab\ops
...

Remove H:\My Documents\MATLAB from the search path and confirm the result:

rmpath('H:\My Documents\MATLAB')
path

MATLAB returns:

MATLABPATH

```
C:\Program Files\MATLAB\R2009a\toolbox\matlab\general
C:\Program Files\MATLAB\R2009a\toolbox\matlab\ops
...
```

Verify the value:

userpath

MATLAB returns:

H:\My Documents\MATLAB

Save changes to the search path:

savepath

View the value:

userpath

MATLAB returns:

```
ans =
```

The value is now cleared. Removing the folder from the search path *and* saving the changes to the path has the same effect as clearing the value for *userpath*. At the next startup, the startup folder will *not* be H:\My Documents\MATLAB, and H:\My Documents\MATLAB will *not* be on the search path.

Assigning *userpath* as the Startup Folder on a UNIX or Macintosh Platform

userpath is set to the default value on a Macintosh platform and you start MATLAB using a bash X11 shell, where smith is the home folder. Set the MATLAB_USE_USERPATH environment variable so that *userpath* will be used as the startup folder:

```
export MATLAB_USE_USERPATH=1
```

From that shell, start MATLAB. After MATLAB starts, verify the current folder in MATLAB:

pwd

MATLAB returns:

/Users/smith/Documents/MATLAB

That is the value defined for *userpath*, which you can confirm:

userpath

MATLAB returns:

/Users/smith/Documents/MATLAB

The *userpath* is at the top of the search path, which you can confirm:

path

MATLAB returns:

. . .

/Users/smith/Documents/MATLAB /Users/smith/Applications/MATLAB/R2009a/toolbox/matlab/general /Users/smith/Applications/MATLAB/R2009a/toolbox/matlab/ops

Adding Folders to the Search Path Upon Startup on a UNIX or Macintosh Platform

userpath is set to the default value on a UNIX platform with a csh shell, where j is the user's home folder.

To add additional folders to the search path upon startup, for example, /home/j/Documents/MATLAB/mine and /home/j/Documents/MATLAB/mine/research, run the following in an X11 terminal:

setenv MATLABPATH '/home/j/Documents/MATLAB/mine':'/home/j/Documents/MATLAB/mine/research'

Separate multiple folders using a : (colon).

MATLAB displays

MATLABPATH

home/j/Documents/MATLAB
home/j/Documents/MATLAB/mine
home/j/Documents/MATLAB/mine/research
home/j/Applications/MATLAB/R2009a/toolbox/matlab/general
home/j/Applications/MATLAB/R2009a/toolbox/matlab/ops
...

See Also addpath, path, pathtool, rmpath, savepath, startup,

Topics in the User Guide:

- "Using the MATLAB Search Path"
- "Startup and Shutdown"

validateattributes

Purpose	Check validity of array	
Syntax	<pre>validateattributes(A, classes, attributes) validateattributes(A, classes, attributes, position) validateattributes(A, classes, attributes, funcname) validateattributes(A, classes, attributes, funcname, varname) validateattributes(A, classes, attributes, funcname, varname,</pre>	
Description	validateattributes(A, classes, attributes) validates that array A belongs to at least one of the classes specified by the classes input and has all of the attributes specified by the attributes input. If the validation succeeds, the command completes without displaying any output and without throwing an error. If the validation does not succeed, MATLAB issues a formatted error message. The classes input is a cell array containing one or more strings from	
	the Class Values on page 2-4341 table shown below. The <i>attributes</i> input is a cell array containing one or more strings from the Attribute Values on page 2-4342 table shown below. Size validation requires two inputs: the 'size' keyword and the length of each dimension (e.g., {'size', [4,3,7]}). Value range validation requires two inputs for each aspect of the range being validated (e.g., {'>', 10, '<=', 65}).	
	validateattributes(A, classes, attributes, position) validates array A and, if the validation fails, displays an error message that includes the position of the failing variable in the function argument list. The <i>position</i> input must be a positive integer.	
	<pre>validateattributes(A, classes, attributes, funcname) validates array A and, if the validation fails, displays an error message that includes the name of the function performing the validation (funcname). The funcname input must be a string.</pre>	

validateattributes(A, classes, attributes, funcname, varname) validates array A and, if the validation fails, displays an error message that includes the name of the function performing the validation (funcname), and the name of the variable being validated (varname). The funcname and varname inputs must be strings enclosed in single quotation marks.

validateattributes (A, classes, attributes, funcname, varname, position) validates array A and, if the validation fails, displays an error message that includes the name of the function performing the validation (funcname), the name of the variable being validated (varname), and the position of this variable in the function argument list (position). The funcname and varname inputs must be strings enclosed in single quotation marks. The position input must be a positive integer.

classes Argument	Contents of Array A
'numeric'	Any numeric value
'single'	Single-precision number
'double'	Double-precision number
'int8'	Signed 8-bit integer
'int16'	Signed 16-bit integer
'int32'	Signed 32-bit integer
'int64'	Signed 64-bit integer
'uint8'	Unsigned 8-bit integer
'uint16'	Unsigned 16-bit integer
'uint32'	Unsigned 32-bit integer
'uint64'	Unsigned 64-bit integer
'logical'	Logical true or false

Class Values

Class Values (Continued)

classes Argument	Contents of Array A		
''char'	Character or string		
'struct'	MATLAB structure		
'cell'	Cell array		
'function_handle'	Scalar function handle		
class name	Object of any MATLAB class		

Attribute Values

attributes Argument	Description of array A	
'>', N	Array in which all values are greater than N.	
'>=', N	Array in which all values are greater than or equal to N.	
'<', N	Array in which all values are less than N.	
'<=', N	Array in which all values are lass than or equal to N.	
' 2d '	Array having dimensions M-by-N (includes scalars, vectors, 2-D matrices, and empty arrays)	
'binary'	Array of ones and zeros	
'column'	Array having dimensions N-by-1	
'even'	Numeric or logical array in which all elements are even (includes zero)	
'finite'	Numeric array in which all elements are finite	
'integer'	Numeric array in which all elements are integer-valued	
'nonempty'	Array having no dimension equal to zero	

Attribute Values (Continued)

attributes Argument	Description of array A
'nonnan'	Numeric array in which there are no elements equal to NaN (Not a Number)
'nonnegative	Numeric array in which all elements are zero or greater than zero
'nonsparse'	Array that is not sparse
'nonzero'	Numeric or logical array in which all elements are less than or greater than zero
'odd'	Numeric or logical array in which all elements are odd integers
'positive'	Numeric or logical array in which all elements are greater than zero
'real'	Numeric array in which all elements are real
'row'	Array having dimensions 1-by-N
'scalar'	Array having dimensions 1-by-1
'size', [M,N,]	Array having dimensions M-by-N-by
'vector'	Array having dimensions N-by-1 or 1-by-N (includes scalar arrays)

Numeric properties, such as positive and nonnan, do not apply to strings. If you attempt to validate numeric properties on a string, validateattributes generates an error.

Examples Example 1

In this example, the empl_profile1 function compares the values passed in each argument to the specified classes and attributes and throws an error if they are not correct:

```
function empl_profile1(empl_id, empl_info, healthplan, ...
vacation)
validateattributes(empl_id, {'numeric'}, ...
{'integer', 'nonempty'});
validateattributes(empl_info, {'struct'}, {'vector'});
validateattributes(healthplan, {'cell', 'char'}, ...
{'vector'});
validateattributes(vacation, {'numeric'}, ...
{'nonnegative', 'scalar'});
```

Call the empl_profile1 function, passing the expected argument types, and the example completes without error:

```
empl_id = 51723;
empl_info.name = 'John Miller';
empl_info.address = '128 Forsythe St.';
empl_info.town = 'Duluth'; empl_info.state='MN';
empl profile1(empl id, empl info, 'HCP Medical Plus', 14.3)
```

If you accidentally pass the argument values out of their correct sequence, MATLAB throws an error in response to the first argument that is not a match:

```
empl_profile1(empl_id, empl_info, 14.3, 'HCP Medical Plus')
??? Error using ==> empl_profile1 at 6
Expected input to be one of these types:
   cell, char
Instead its type was double.
```

Example 2

Write a new function empl_profile2 that displays the function name, variable name, and position of the argument:

```
function empl_profile2(empl_id, empl_info, healthplan, ...
    vacation)
validateattributes(empl_id, ...
    {'numeric'}, {'integer', 'nonempty'}, ...
    mfilename, 'Employee Identification', 1);
validateattributes(empl_info, ...
    {'struct'}, {'vector'}, ...
    mfilename, 'Employee Info', 2);
validateattributes(healthplan, ...
    {'cell', 'char'}, {'vector'}, ...
    mfilename, 'Health Plan', 3);
validateattributes(vacation, ...
    {'numeric'}, {'nonnegative', 'scalar'}, ...
    mfilename, 'Vacation Accrued', 4);
```

Call empl_profile2 with the argument values out of sequence. MATLAB throws an error that includes the name of the function validating the attributes, the name of the variable that was in error, and its position in the input argument list:

```
??? Error using ==> empl_profile2
Expected input number 3, Health Plan, to be one of
these types:
    cell, char
Instead its type was double.
Error in ==> empl_profile2 at 12
validateattributes(healthplan, ...
```

Example 3

Write a new function empl_profile3 that checks the input parameters with inputParser. Use validateattributes as the validating function for the inputParser methods:

```
function empl_profile3(empl_id, varargin)
p = inputParser;
% Validate the input arguments.
addRequired(p, 'empl_id', ...
@(x)validateattributes(x, {'numeric'}, {'integer'}));
addOptional(p, 'empl_info', '', ...
@(x)validateattributes(x, {'struct'}, {'nonempty'}));
addParamValue(p, 'health', 'HCP Medical Plus', ...
@(x)validateattributes(x, {'cell', 'char'}, ...
{'vector'}));
addParamValue(p, 'vacation', [], ...
@(x)validateattributes(x, {'numeric'}, ...
{'nonnegative', 'scalar'}));
parse(p, empl_id, varargin{:});
p.Results
```

Call empl_profile3 using appropriate input arguments:

```
empl_info.name = 'John Miller';
empl_info.address = '128 Forsythe St.';
empl_info.town = 'Duluth'; empl_info.state='MN';
empl_profile3(51723, empl_info, 'vacation', 14.3)
ans =
    empl_id: 51723
    empl_info: [1x1 struct]
        health: 'HCP Medical Plus'
        vacation: 14.3000
```

Call empl_profile3 using a character string where a structure is expected:

```
empl_profile3(51723, empl_info.name, 'vacation', 14.3)
??? Error using ==> empl_profile3 at 12
Argument 'empl_info' failed validation with error:
Expected input to be one of these types:
```

struct

Instead its type was char.

Example 4

Create a 4-by-2-by-6 array and then validate its size:

```
x = rand(4,2,6);
```

validateattributes(x, {'numeric'}, {'size', [4,2,6]});

Create an array of integers between 50 and 200 and then validate that these values are within the intended range:

```
y = uint8(50:10:200);
validateattributes(y, {'uint8'}, {'>=', 50, '<=', 200})</pre>
```

This next statement fails for y(end):

```
validateattributes(y, {'uint8'}, {'>=', 50, '<', 200})
??? Expected input to be an array with all of the
values < 200.</pre>
```

Example 5

Generate a new array z and validate that it is a 4-by-2-by-6 nonsparse array of class double, with all elements being between 0.005 and 50, inclusive:

```
z = rand(4,2,6) * 50;
validateattributes(z, {'numeric', 'double'}, ...
{'<', 50, 'size', [4 2 6], 'nonsparse', '>=', .005});
There are several things to note in the above statement:
```

- All class arguments are enclosed in just one set of curly braces {}. All attribute arguments the same way.
- The placement of the <, <=, >, and >= arguments in the argument list is unimportant. However, you must immediately follow any of these arguments with the numeric argument it relates to.
- The placement of the 'size' argument in the argument list is unimportant. However, you must immediately follow this argument with the numeric vector argument it relates to.

If you add to this a requirement that z be two-dimensional, validateattributes throws an error because z has three dimensions:

```
validateattributes(z, {'double'}, ...
{z, '<', 50, 'size', [4 2 6], '2d', 'positive', '>', 0});
Warning: Failed to find attribute in list.
??? Expected input to be two-dimensional.
```

See Also validatestring, is*, isa, inputParser

Purpose	Check validity of text string					
Syntax	<pre>validstr = validatestring(str, strarray) validstr = validatestring(str, strarray, position) validstr = validatestring(str, strarray, funname) validstr = validatestring(str, strarray, funname, varname) validstr = validatestring(str, strarray, funname, varname,</pre>					
Description	<pre>validstr = validatestring(str, strarray) checks the validity of text string str. If str matches one or more of the text strings in the cell array strarray, MATLAB returns the matching string in validstr. If str does not match any of the strings in strarray, MATLAB issues a formatted error message. MATLAB compares the strings without respect to letter case.</pre>					

Type of Match	Example — Match 'ball' with	Return Value
Exact match	ball, barn, bell	ball
Partial match (leading characters)	balloon, barn	balloon
Multiple partial matches where each string is a subset of another	ballo, balloo, balloon	ballo (shortest match)
Multiple partial matches where strings are unique	balloon, ballet	Error
No match	barn, bell	Error

This table shows how validatestring determines what value to return.

validstr = validatestring(str, strarray, position) checks the validity of text string str and, if the validation fails, displays an error message that includes the position of the failing variable in the function argument list. The position input must be a positive integer. validstr = validatestring(str, strarray, funname) checks the validity of text string str and, if the validation fails, displays an error message that includes the name of the function performing the validation (funname). The funname input must be a string enclosed in single quotation marks.

validstr = validatestring(str, strarray, funname, varname) checks the validity of text string str and, if the validation fails, displays an error message that includes the name of the function performing the validation (funname) and the name of the variable being validated (varname). The funname and varname inputs must be strings enclosed in single quotation marks.

validstr = validatestring(str, strarray, funname, varname, position) checks the validity of text string str and, if the validation fails, displays an error message that includes the name of the function performing the validation (funname), the name of the variable being validated (varname), and the position of this variable in the function argument list (position). The funname and varname inputs must be strings enclosed in single quotation marks. The position input must be a positive integer.

Examples Example 1

Use validatestring to find the word won in the cell array of strings:

```
validatestring('won', {'wind', 'won', 'when'})
ans =
    won
```

Replace the word won with wonder in the string array. Because the leading characters of the input string and wonder are the same, validatestring finds a partial match between the two words and returns the full word wonder:

```
validatestring('won', {'wind', 'wonder', 'when'})
ans =
    wonder
```

If there is more than one partial match, and each string in the array is a subset or superset of the others, validatestring returns the shortest matching string:

```
validatestring('wond', {'won', 'wonder', 'wonderful'})
ans =
    wonder
```

However, if each string in the array is not subset or superset of each other, MATLAB throws an error because there is no exact match and it is not clear which of the two partial matches should be returned:

```
validatestring('wond', {'won', 'wonder', 'wondrous'})
??? Error using ==> validatestring at 89
Function VALIDATESTRING expected its input argument to
   match one of these strings:
   won, wonder, wondrous
```

The input, 'wond', matched more than one valid string.

Example 2

In this example, the get_flight_numbers function returns the flight numbers for routes between two cities: a point of origin and point of destination. The function uses validatestring to see if the origin and destination are among those covered by the airline. If not, an error message is displayed:

```
function get_flight_numbers(origin, destination)
% Only part of the airline's flight data is shown here.
flights.chi2rio = [503, 196, 331, 373, 1475];
flights.chi2par = [718, 9276, 172, 903, 7724 992, 1158];
flights.chi2hon = [9193, 880, 471, 391];
routes = {'Athens', 'Paris', 'Chicago', 'Sydney', ...
'Cancun', 'London', 'Rio de Janeiro', 'Honolulu', ...
'Rome', 'New York City'};
orig = ''; dest = '';
```

```
% Does the airline cover these cities?
   trv
      orig = validatestring(origin, routes);
      dest = validatestring(destination, routes);
   catch
      % If not covered, then display error message.
      if isempty(orig)
         fprintf(...
            'We have no flights with origin: %s.\n', ...
            origin)
      elseif isempty(dest)
         fprintf('%s%s%s.\n', 'We have no flights ', ...
                 'with destination: ', destination)
      end
   return
   end
% If covered, display the flights from 'orig' to 'dest'.
fprintf(...
   'Flights available from %s to %s are:\n', orig, dest)
reply = flights.([lower(orig(1:3)) '2' lower(dest(1:3))]);
fprintf(' Flight %d\n', reply)
```

Enter a point of origin that is not covered by this airline:

get_flight_numbers('San Diego', 'Rio de Janeiro')
ans =
We have no flights with origin: San Diego.

Enter a destination that is misspelled:

get_flight_numbers('Chicago', 'Reo de Janeiro')
ans =
We have no flights with destination: Reo de Janeiro.

Enter a route that is covered:

```
get_flight_numbers('Chicago', 'Rio de Janeiro')
ans =
Flights available from Chicago to Rio de Janeiro are:
   Flight 503
   Flight 196
   Flight 331
   Flight 373
   Flight 1475
```

Example 3

Rewrite the try-catch block of Example 2 by adding funname, varname, and position arguments to the call to validatestring and replacing the return statement with rethrow:

```
% See if the cities entered are covered by this airline.
try
   orig = validatestring(...
      origin, routes, mfilename, 'Flight Origin', 1);
   dest = validatestring(...
      destination, routes, mfilename, ...
        'Flight Destination', 2);
catch e
   % If not covered, then display error message.
   if isempty(orig)
       fprintf(...
          'We have no flights with origin: %s.\n', ...
          origin)
   elseif isempty(dest)
       fprintf('%s%s%s.\n', 'We have no flights ', ...
               'with destination: ', destination)
   end
   rethrow(e);
end
```

In response to the rethrow command, MATLAB displays an error message that includes the function name get_flight_numbers, the

failing variable name Flight Destination, and its position in the argument list, 2: get flight numbers('Chicago', 'Reo de Janeiro') We have no flights with destination: Reo de Janeiro. ??? Error using ==> validatestring at 89 Function GET FLIGHT NUMBERS expected its input argument number 2, Flight Destination, to match one of these strings: Athens, Paris, Chicago, Sydney, Cancun, London, Rio de Janeiro, Honolulu, Rome The input, 'Reo de Janeiro', did not match any of the valid strings. Error in ==> get flight numbers at 17 dest = validatestring(destination, routes, mfilename, 'destination', 2); See Also validateattributes, is*, isa, inputParser

Purpose	Return values of containers.Map object					
Syntax	<pre>v = values(M) v = values(M, keys)</pre>					
Description	v = values(M) returns in cell array v the values that correspond to all keys in Map object M.					
	<pre>v = values(M, keys) returns in cell array v, those values in Map object M that correspond to the keys specified by the keys argument.</pre>					
	Read more about Map Containers in the MATLAB Programming Fundamentals documentation.					
Examples	Create a Map object of four US states and their capital cities: US_Capitals = containers.Map({'Georgia', 'Alaska', 'Vermont', 'Oregon'}, {'Atlanta', 'Juneau', 'Montpelier', 'Salem'})					
	Find the capital cities of all states contained in the map:					
	<pre>v = values(US_Capitals)</pre>					
	v = 'Juneau' 'Atlanta' 'Salem' 'Montpelier'					
	Find the capital cities of selected states:					
	<pre>= values(US_Capitals, {'Oregon', 'Alaska'}) v =</pre>					
	'Salem' 'Juneau'					
See Also	containers.Map,keys(Map),size(Map),length(Map),isKey(Map), remove(Map),handle					

vander

Purpose	Vandermonde matrix						
Syntax	A = vander(v)						
Description	A = vander(v) returns the Vandermonde matrix whose columns are powers of the vector v, that is, $A(i,j) = v(i)^{(n-j)}$, where n = length(v).						
Examples	vander(1:.5:3)						
	ans =						
	1.0000	1.0000	1.0000	1.0000	1.0000		
	5.0625	3.3750	2.2500	1.5000	1.0000		
	16.0000	8.0000	4.0000	2.0000	1.0000		
	39.0625	15.6250	6.2500	2.5000	1.0000		
	81.0000	27.0000	9.0000	3.0000	1.0000		
See Also	gallery						

Purpose	Variance
Syntax	V = var(X) V = var(X,1) V = var(X,w) V = var(X,w,dim)
Description	V = var(X) returns the variance of X for vectors. For matrices, var(X) is a row vector containing the variance of each column of X. For N-dimensional arrays, var operates along the first nonsingleton dimension of X. The result V is an unbiased estimator of the variance of the population from which X is drawn, as long as X consists of independent, identically distributed samples.
	var normalizes V by N-1 if N>1, where N is the sample size. This is an unbiased estimator of the variance of the population from which X is drawn, as long as X consists of independent, identically distributed samples. For N=1, V is normalized by N.
	V = var(X,1) normalizes by N and produces the second moment of the sample about its mean.var(X,0) is equivalent to var(X).
	V = var(X,w) computes the variance using the weight vector w. The length of w must equal the length of the dimension over which var operates, and its elements must be nonnegative. The elements of w must be positive. var normalizes w to sum of 1.
	V = var(X,w,dim) takes the variance along the dimension dim of X. Pass in 0 for w to use the default normalization by N-1, or 1 to use N.
	The variance is the square of the standard deviation (STD).
See Also	corrcoef, cov, mean, median, std

var (timeseries)

Purpose	Variance of timeseries data
Syntax	ts_var = var(ts) ts_var = var(ts,'PropertyName1',PropertyValue1,)
Description	ts_var = var(ts) returns the variance of ts.data. When ts.Data is a vector, ts_var is the variance of ts.Data values. When ts.Data is a matrix, ts_var is a row vector containing the variance of each column of ts.Data (when IsTimeFirst is true and the first dimension of ts is aligned with time). For the N-dimensional ts.Data array, var always operates along the first nonsingleton dimension of ts.Data.
	<pre>ts_var = var(ts, 'PropertyName1', PropertyValue1,) specifies the following optional input arguments:</pre>
	 'MissingData' property has two possible values, 'remove' (default) or 'interpolate', indicating how to treat missing data during the calculation.
	• 'Quality' values are specified by an integer vector, indicating which quality codes represent missing samples (for vector data) or missing observations (for data arrays with two or more dimensions).
	 'Weighting' property has two possible values, 'none' (default) or 'time'. When you specify 'time', larger time values correspond to larger weights.
Examples	The following example shows how to calculate the variance values of a multi-variate timeseries object.
	l Load a 24-by-3 data array.
	load count.dat
	2 Create a timeseries object with 24 time values.
	<pre>count_ts = timeseries(count,[1:24],'Name','CountPerSecond')</pre>

3 Calculate the variance of each data column for this timeseries object.

```
var(count_ts)
ans =
    1.0e+003 *
    0.6437    1.7144    4.6278
```

The variance is calculated independently for each data column in the timeseries object.

See Also iqr (timeseries), mean (timeseries), median (timeseries), std (timeseries), timeseries

varargin

Purpose	Variable length input argument list
Syntax	<pre>function y = bar(varargin)</pre>
Description	<pre>function y = bar(varargin) accepts a variable number of arguments into function bar.m.</pre>
	The varargin statement is used only inside a function to contain optional input arguments passed to the function. The varargin argument must be declared as the last input argument to a function, collecting all the inputs from that point onwards. In the declaration, varargin must be lowercase.
Examples	Example 1
	Write a function that displays the expected and optional arguments you pass to it
	<pre>function vartest(argA, argB, varargin)</pre>
	optargin = size(varargin,2); stdargin = nargin - optargin;
	fprintf('Number of inputs = %d\n', nargin)
	fprintf(' Inputs from individual arguments(%d):\n', stdargin)
	if stdargin >= 1 fprintf(' %d\n', argA) end
	if stdargin == 2 fprintf(' %d\n', argB) end
	fprintf(' Inputs packaged in varargin(%d):\n', optargin) for k= 1 : size(varargin,2) fprintf(' %d\n', varargin{k}) end

Call this function and observe that the MATLAB software extracts those arguments that are not individually-specified from the varargin cell array:

```
vartest(10,20,30,40,50,60,70)
Number of inputs = 7
Inputs from individual arguments(2):
    10
    20
Inputs packaged in varargin(5):
    30
    40
    50
    60
    70
```

Example 2

The function

```
function myplot(x,varargin)
plot(x,varargin{:})
```

collects all the inputs starting with the second input into the variable varargin. myplot uses the comma-separated list syntax varargin{:} to pass the optional parameters to plot. The call

```
myplot(sin(0:.1:1),'color',[.5 .7 .3],'linestyle',':')
```

results in varargin being a 1-by-4 cell array containing the values 'color', [.5 .7 .3], 'linestyle', and ':'.

See Also varargout, nargin, nargout, nargchk, nargoutchk, inputname

varargout

Purpose	Variable length output argument list
Syntax	function varargout = foo(n)
Description	<pre>function varargout = foo(n) returns a variable number of arguments from function foo.m.</pre>
	The varargout statement is used only inside a function to contain the optional output arguments returned by the function. The varargout argument must be declared as the last output argument to a function, collecting all the outputs from that point onwards. In the declaration, varargout must be lowercase.
Examples	The function
	<pre>function [s,varargout] = mysize(x) nout = max(nargout,1)-1; s = size(x); for k=1:nout, varargout(k) = {s(k)}; end</pre>
	returns the size vector and, optionally, individual sizes. So
	<pre>[s,rows,cols] = mysize(rand(4,5));</pre>
	returns $s = [4 5]$, rows = 4, cols = 5.
See Also	varargin, nargin, nargout, nargchk, nargoutchk, inputname

vectorize

Purpose	Vectorize expression
Syntax	vectorize(s) vectorize(fun)
Description	<code>vectorize(s)</code> where s is a string expression, inserts a . before any ^, * or / in s. The result is a character string.
	vectorize(fun) when fun is an inline function object, vectorizes the formula for fun. The result is the vectorized version of the inline function.
See Also	inline, cd, dbtype, delete, dir, path, what, who

ver

Purpose	Version information for MathWorks products
GUI Alternatives	As an alternative to the ver function, select Help > About in any tool that has a Help menu.
Syntax	ver ver product v = ver('product')
Description	ver displays a header containing the current MathWorks product family version number, license number, operating system, and version of Sun Microsystems JVM software for the MATLAB product. This is followed by the version numbers for MATLAB, Simulink, if installed, and all other installed MathWorks products.
	ver product displays the MathWorks product family header information followed by the current version number for product. The name product corresponds to the folder name that holds the Contents.m file for that product. For example, Contents.m for the Control System Toolbox product resides in the control folder. You therefore use ver control to obtain the version of this toolbox.
	v = ver('product') returns the version information to structure array, v , having fields Name, Version, Release, and Date.
Remarks	To use ver with your own collection of files, see "Creating a Help Summary for Your Program Files".
Examples	Using R2009b, return version information for MathWorks products, and specifically the Control System Toolbox product:
	ver control
	MATLAB returns:
	MATLAB Version 7.9.0.3512 (R2009b)
	MATLAB License Number: [not shown]

m

Operating System: Microsoft Windows XP Version 5.1 (Build 2600: Service Pack 3)		
Java VM Version: Java 1.6.0_12-b04 with Sun Microsyst	ems Inc. Java HotSpo	ot(TM) Client VM mixed
Control System Toolbox	Version 8.3	(R2009b)

Return version information for the Control System Toolbox product in a structure array, $\boldsymbol{v}.$

```
v = ver('control')
v =
Name: 'Control System Toolbox'
Version: '8.4'
Release: '(R2009b)'
Date: '24-Sep-2009'
```

Display version information for MathWorks 'Real-Time' products:

verctrl

Purpose	Source control actions (Windows platforms)
GUI Alternatives	As an alternative to the verctrl function, use Source Control in the File menu of the Editor, the Simulink product, or the Stateflow product, or in the context menu of the Current Folder browser.
Syntax	<pre>verctrl('action',{'filename1','filename2',},0) result=verctrl('action',{'filename1','filename2',},0) verctrl('action','filename',0) result=verctrl('isdiff','filename',0) list = verctrl('all_systems')</pre>
Description	<pre>verctrl('action',{'filename1', 'filename2',},0) performs the source control operation specified by 'action' for a single file or multiple files. Enter one file as a string; specify multiple files using a cell array of strings. Use the full paths for each file name and include the extensions. Specify 0 as the last argument. Complete the resulting dialog box to execute the operation. Available values for 'action' are</pre>

as follows:

action	
Argument	Purpose
'add'	Adds files to the source control system. Files can be open in the Editor or closed when added.
'checkin'	Checks files into the source control system, storing the changes and creating a new version.
'checkout'	Retrieves files for editing.
'get'	Retrieves files for viewing and compiling, but not editing. When you open the files, they are labeled as read-only.
'history'	Displays the history of files.

action Argument	Purpose
'remove'	Removes files from the source control system. It does not delete the files from disk, but only from the source control system.
'runscc'	Starts the source control system. The file name can be an empty string.
'uncheckout'	Cancels a previous checkout operation and restores the contents of the selected files to the precheckout version. All changes made to the files since the checkout are lost.

result=verctrl('action',{'filename1','filename2',....},0)
performs the source control operation specified by 'action' on a single
file or multiple files. The action can be any one of: 'add', 'checkin',
'checkout', 'get', 'history', or 'undocheckout'. result is a logical
1 (true) when you complete the operation by clicking OK in the resulting
dialog box, and is a logical 0 (false) when you abort the operation by
clicking Cancel in the resulting dialog box.

verctrl('action', 'filename',0) performs the source control
operation specified by 'action' for a single file. Use the absolute path
for 'filename'. Specify 0 as the last argument. Complete any resulting
dialog boxes to execute the operation. Available values for 'action'
are as follows:

action Argument	Purpose
'showdiff'	Displays the differences between a file and the latest checked in version of the file in the source control system.
'properties'	Displays the properties of a file.

result=verctrl('isdiff', 'filename',0) compares filename with the latest checked in version of the file in the source control system. result is a logical 1 (true) when the files are different, and is a logical 0 (false) when the files are identical. Use the full path for 'filename'. Specify 0 as the last argument.

list = verctrl('all_systems') displays in the Command Window a
list of all source control systems installed on your computer.

Examples Check In a File

Check in D:\file1.ext to the source control system:

```
result = verctrl('checkin', 'D:\file1.ext', 0)
```

This opens the Check in file(s) dialog box. Click **OK** to complete the check in. MATLAB displays

```
result = 1
```

indicating the checkin was successful.

Add Files to the Source Control System

Add D:\file1.ext and D:\file2.ext to the source control system.

```
verctrl('add',{'D:\file1.ext','D:\file2.ext'}, 0)
```

This opens the Add to source control dialog box. Click **OK** to complete the operation.

Display the Properties of a File

Display the properties of D:\file1.ext.

```
verctrl('properties', 'D:\file1.ext', 0)
```

This opens the source control properties dialog box for your source control system. The function is complete when you close the properties dialog box.

Show Differences for a File

To show the differences between the version of file1.ext that you just edited and saved, with the last version in source control, run

```
verctrl('showdiff','D:\file1.ext',0)
```

MATLAB displays differences dialog boxes and results specific to your source control system. After checking in the file, if you run this statement again, MATLAB displays

??? The file is identical to latest version under source control.

List All Installed Source Control Systems

To view all of the source control systems installed on your computer, type

```
list = verctrl ('all_systems')
```

MATLAB displays all the source control systems currently installed on your computer. For example:

```
list =
'Microsoft Visual SourceSafe'
'ComponentSoftware RCS'
```

See Also checkin, checkout, undocheckout, cmopts

"Source Control Interface on Microsoft Windows" in MATLAB Desktop Tools and Development Environment documentation

verLessThan

Purpose	Compare toolbox version to specified version string
Syntax	verLessThan(toolbox, version)
Description	verLessThan(toolbox, version) returns logical 1 (true) if the version of the toolbox specified by the string toolbox is older than the version specified by the string version, and logical 0 (false) otherwise. Use this function when you want to write code that can run across multiple versions of the MATLAB software, when there are differences in the behavior of the code in the different versions.
	The toolbox argument is a string enclosed within single quotation marks that contains the name of a MATLAB toolbox folder. The version argument is a string enclosed within single quotation marks that contains the version to compare against. This argument must be in the form major[.minor[.revision]], such as 7, 7.1, or 7.0.1. If toolbox does not exist, MATLAB generates an error.
	To specify toolbox, find the folder that holds the Contents.m file for the toolbox and use that folder name. To see a list of all toolbox folder names, enter the following statement in the MATLAB Command Window:
	dir([matlabroot '/toolbox'])
Remarks	The verLessThan function is available with MATLAB Version 7.4 and subsequent versions. If you are running a version of MATLAB prior to 7.4, you can download the verLessThan function from the following MathWorks Technical Support solution. You must be running MATLAB Version 6.0 or higher to use this function:
	http://www.mathworks.com/support/solutions/data/1-38LI61.html?solution=1-
Examples	These examples illustrate usage of the verLessThan function.
	Example 1 – Checking For the Minimum Required Version
	if verLessThan('simulink', '4.0') error('Simulink 4.0 or higher is required.');

end

Example 2 – Choosing Which Code to Run

```
if verLessThan('matlab', '7.0.1')
% -- Put code to run under MATLAB 7.0.0 and earlier here --
else
% -- Put code to run under MATLAB 7.0.1 and later here --
end
```

Example 3 - Looking Up the Folder Name

Find the name of the Data Acquisition Toolbox folder:

```
dir([matlabroot '/toolbox/d*'])
```

daq	database	des	distcomp	dotnetbuilder
dastudio	datafeed	dials	dml	dspblks

Use the toolbox folder name, daq, to compare the Data Acquisition Toolbox software version that MATLAB is currently running against version number 3:

See Also ver, version, license, ispc, isunix, ismac, dir

version

Purpose	Version number for MATLAB and libraries
Syntax	<pre>version version('-date') version('-description') version('-release') version('-java') version -versionOption v = version('-versionOption')</pre>
Description	version displays the version and release number for the MATLAB software currently running.
	version('-date') displays the release date for the MATLAB software.
	version('-description') displays a description of the version. Usually, the description is for special versions, such as beta versions.
	version('-release') displays the release number for the MATLAB software currently running.
	version('-java') displays the version of the Sun Microsystems JVM software that MATLAB is using.
	version -versionOption is an alternate form of the syntax.
	<pre>v = version('-versionOption') returns a string containing the result of version.</pre>
Examples	Display the version:
	version
	MATLAB returns:
	7.9.0.2601 (R2009b)

Display the release, prefaced by a descriptor:

	['Release R' version('-release')]
	MATLAB returns:
	Release R2009b
	View the Java version:
	version -java
	MATLAB returns:
	Java 1.6.0_12-b04 with Sun Microsystems Inc. Java HotSpot(TM) Clien
Alternatives	To view version information, select Help > About MATLAB in the MATLAB desktop.
See Also	computer ver verlessthan whatsnew
How To	• "Check for Updates"
	 "Using a Different Version of JVM Software"

vertcat

Purpose	Concatenate arrays vertically
Syntax	C = vertcat(A1, A2,)
Description	C = vertcat(A1, A2,) vertically concatenates matrices A1, A2, and so on. All matrices in the argument list must have the same number of columns.
	vertcat concatenates N-dimensional arrays along the first dimension. The remaining dimensions must match.
	MATLAB calls $C = vertcat(A1, A2,)$ for the syntax $C = [A1; A2;]$ when any of A1, A2, etc. is an object.
Examples	Create a 5-by-3 matrix, A, and a 3-by-3 matrix, B. Then vertically concatenate A and B.
	A = magic(5); % Create 5-by-3 matrix, A A(:, 4:5) = []
	A =
	$\begin{array}{cccccccccccccccccccccccccccccccccccc$
	B = magic(3)*100 % Create 3-by-3 matrix, B
	В =
	800 100 600 300 500 700 400 900 200

С	=	verto	cat(A,	B)	% Vertically concatenate A and B
С	=				
		17	24	1	
		23	5	7	
		4	6	13	
		10	12	19	
		11	18	25	
	8	800	100	600	
	З	800	500	700	
	4	00	900	200	

horzcat, cat

vertcat (timeseries)

Purpose	Vertical concatenation of timeseries objects
Syntax	<pre>ts = vertcat(ts1,ts2,)</pre>
Description	ts = vertcat(ts1,ts2,) performs
	ts = [ts1;ts2;]
	This operation appends timeseries objects. The time vectors must not overlap. The last time in ts1 must be earlier than the first time in ts2. The data sample size of the timeseries objects must agree.
See Also	timeseries

Purpose	Vertical concatenation for tscollection objects
Syntax	<pre>tsc = vertcat(tsc1,tsc2,)</pre>
Description	<pre>tsc = vertcat(tsc1,tsc2,) performs</pre>
	tsc = [tsc1;tsc2;]
	This operation appends tscollection objects. The time vectors must not overlap. The last time in tsc1 must be earlier than the first time in tsc2. All tscollection objects to be concatenated must have the same timeseries members.
See Also	horzcat (tscollection), tscollection

TriRep.vertexAttachments

Purpose	Return simplices attached to specified vertices		
Syntax	<pre>SI = vertexAttachments(TR, VI)</pre>		
Description	SI = vertexAttachments(TR, VI) returns the vertex-to-simplex information for the specified vertices VI. In relation to 2-D triangulations, if the triangulation has a consistent orientation the triangles in each cell will be ordered consistently around each vertex.		
Input	TR	Triangulation representation	
Arguments	VI	VI is a column vector of indices into the array of points representing the vertex coordinates, TR.X. The simplices associated with vertex i are the i'th entry in the cell array. If VI is not specified the vertex-simplex information for the entire triangulation is returned.	
Output Arguments	SI	Cell array of indices of the simplices attached to a vertex. A cell array is used to store the information because the number of simplices associated with each vertex can vary. The simplices associated with vertex i are in the i'th entry in the cell array SI.	
Definitions	A simplex is a triangle/tetrahedron or higher dimensional equivalent.		
Examples	Example 1		
	Load a 2-D triangulation and use TriRep to compute the vertex-to-triangle relations.		
	load trimesh2d		
	Find the indices of the tetrahedra attached to the first vertex:		

```
Tv = vertexAttachments(trep, 1)
Tv{:}
```

Example 2

Perform a direct query of a 2-D triangulation created using DelaunayTri.

x = rand(20,1); y = rand(20,1); dt = DelaunayTri(x,y);

Find the triangles attached to vertex 5:


t = vertexAttachments(dt,5);

Plot the triangulation:

triplot(dt);
hold on;

Plot the triangles attached to vertex 5 (in red):

triplot(dt(t{:},:),x,y,'Color','r'); hold off;




See Also

DelaunayTri

Purpose	Viewpoint specification
Syntax	<pre>view(az,el) view([az,el]) view([x,y,z]) view(2) view(3) view(ax,) [az,el] = view T = view</pre>
Description	The position of the viewer (the viewpoint) determines the orientation of the axes. You specify the viewpoint in terms of azimuth and elevation, or by a point in three-dimensional space.
	<pre>view(az,el) and view([az,el]) set the viewing angle for a three-dimensional plot. The azimuth, az, is the horizontal rotation about the z-axis as measured in degrees from the negative y-axis. Positive values indicate counterclockwise rotation of the viewpoint. el is the vertical elevation of the viewpoint in degrees. Positive values of elevation correspond to moving above the object; negative values correspond to moving below the object.</pre>
	<pre>view([x,y,z]) sets the viewpoint to the Cartesian coordinates x, y, and z. The magnitude of (x,y,z) is ignored.</pre>
	view(2) sets the default two-dimensional view, az = 0, el = 90.
	<pre>view(3) sets the default three-dimensional view, az = 37.5, e1 = 30.</pre>
	view(ax,) uses axes ax instead of the current axes.
	[az,el] = view returns the current azimuth and elevation.
	T = view returns the current 4-by-4 transformation matrix.
Remarks	Azimuth is a polar angle in the <i>x-y</i> plane, with positive angles indicating counterclockwise rotation of the viewpoint. Elevation is the angle above (positive angle) or below (negative angle) the <i>x-y</i> plane.

This diagram illustrates the coordinate system. The arrows indicate positive directions.



Examples

View the object from directly overhead.

az = 0; el = 90; view(az, el);

Set the view along the *y*-axis, with the *x*-axis extending horizontally and the *z*-axis extending vertically in the figure.

view([0 0]);

Rotate the view about the z-axis by 180° .

az = 180; el = 90; view(az, el);

See Also viewmtx, hgtransform, rotate3d

"Camera Viewpoint" on page 1-109 for related functions

Axes graphics object properties CameraPosition, CameraTarget, CameraViewAngle, Projection

Defining the View for more information on viewing concepts and techniques

Transforming Objects for information on moving and scaling objects in groups

viewmtx

Purpose	View transformation matrices
Syntax	viewmtx T = viewmtx(az,el) T = viewmtx(az,el,phi) T = viewmtx(az,el,phi,xc)
Description	viewmtx computes a 4-by-4 orthographic or perspective transformation matrix that projects four-dimensional homogeneous vectors onto a two-dimensional view surface (e.g., your computer screen).
	T = viewmtx(az,el) returns an <i>orthographic</i> transformation matrix corresponding to azimuth az and elevation el. az is the azimuth (i.e., horizontal rotation) of the viewpoint in degrees. el is the elevation of the viewpoint in degrees. This returns the same matrix as the commands
	view(az,el) T = view

but does not change the current view.

T = viewmtx(az,el,phi) returns a *perspective* transformation matrix. phi is the perspective viewing angle in degrees. phi is the subtended view angle of the normalized plot cube (in degrees) and controls the amount of perspective distortion.

Phi	Description
0 degrees	Orthographic projection
10 degrees	Similar to telephoto lens
25 degrees	Similar to normal lens
60 degrees	Similar to wide-angle lens


T = viewmtx(az,el,phi,xc) returns the perspective transformation matrix using xc as the target point within the normalized plot cube (i.e., the camera is looking at the point xc). xc is the target point that is the center of the view. You specify the point as a three-element vector, xc = [xc,yc,zc], in the interval [0,1]. The default value is xc = [0,0,0].

A four-dimensional homogenous vector is formed by appending a 1 to the corresponding three-dimensional vector. For example, [x,y,z,1] is the four-dimensional vector corresponding to the three-dimensional point [x,y,z].

Examples Determine the projected two-dimensional vector corresponding to the three-dimensional point (0.5,0.0,-3.0) using the default view direction. Note that the point is a column vector.

```
A = viewmtx(-37.5, 30);
x4d = [.5 \ 0 \ -3 \ 1]';
x2d = A*x4d;
x2d = x2d(1:2)
% Vectors that trace the edges of a unit cube are
x = [0]
               0
                  0
                                                    0
        1
            1
                      0
                         1
                            1
                                0
                                   0
                                      1
                                          1
                                             1
                                                1
                                                       0];
y = [0]
        0
           1
               1
                  0
                      0
                         0
                            1
                                1
                                   0
                                      0
                                          0
                                             1
                                                1
                                                    1
                                                       1];
z = [0 \ 0 \ 0]
               0
                  0
                      1
                         1
                            1
                                1
                                   1
                                      1
                                          0
                                             0
                                                1
                                                    1
                                                       0];
% Transform the points in these vectors to the
% screen, then plot the object.A = viewmtx(-37.5,30);
[m,n] = size(x);
x4d = [x(:), y(:), z(:), ones(m*n, 1)]';
x2d = A*x4d;
x^2 = zeros(m,n); y^2 = zeros(m,n);
x2(:) = x2d(1,:);
y2(:) = x2d(2,:);
plot(x2,y2)
```

viewmtx



Use a perspective transformation with a 25 degree viewing angle:

```
A = viewmtx(-37.5,30,25);

x4d = [.5 0 -3 1]';

x2d = A*x4d;

x2d = x2d(1:2)/x2d(4) % Normalize


x2d =

0.1777

-1.8858
```

Transform the cube vectors to the screen and plot the object:

```
A = viewmtx(-37.5,30,25);
[m,n] = size(x);
x4d = [x(:),y(:),z(:),ones(m*n,1)]';
x2d = A*x4d;
x2 = zeros(m,n); y2 = zeros(m,n);
x2(:) = x2d(1,:)./x2d(4,:);
y2(:) = x2d(2,:)./x2d(4,:);
plot(x2,y2)
```



- See Also view | hgtransform
- **Tutorials** Defining the View

visdiff

Purpose	Compare two text files, MAT-Files, binary files, or folders
Syntax	visdiff('fname1', 'fname2')
Description	 visdiff('fname1', 'fname2') opens the File and Folder Comparisons tool and presents the differences between the two files or folders. Either ensure that the two files or folders appear on the MATLAB path, or provide the full path for each file or folder. Note MATLAB supports displaying the differences in the File and Folder Comparisons tool only when you have Java software installed.
	Folder Comparisons tool only when you have sava software instaned.

Examples Specifying Files or Folders to Compare

The visdiff function accepts fully qualified file names, relative file names, or names of files on the MATLAB path.

If the files you want to compare appear on the MATLAB path or in the current folder, you can specify the file names without the full path, for example:

```
visdiff('lengthofline.m','lengthofline2.m')
```

or

```
visdiff('lengthofline','lengthofline2')
```

If the files you want to compare are not on the path, either specify the full path to each file, or add the folders to the path.

For example, to specify the fully qualified file names to compare two example files:

```
visdiff(fullfile(matlabroot,'toolbox','matlab','demos','gatlin.mat'), ...
fullfile(matlabroot,'toolbox','matlab','demos','gatlin2.mat'))
```

Specify the full path to files as follows:

```
visdiff('C:\Work\comp\lengthofline.m', 'C:\Work\comp\lengthofline2.m')
```

You can specify paths to files relative to the current folder. For the preceding example, if the current folder is Work, then the relative paths are:

```
visdiff('comp\lengthofline.m', 'comp\lengthofline2.m')
```

Compare Two Text Files

To view a comparison of the two example files, lengthofline.m and lengthofline2.m:

```
visdiff(fullfile(matlabroot, 'help', 'techdoc', 'matlab_env',...
'examples', 'lengthofline.m'), fullfile(matlabroot, 'help',...
```

📣 File and Folder Comparisons - C:\Work\comp\lengthofline2.m vs. C:\Work\comp\lengthofline.m _ 🗆 🗵 × 5 × <u>File Edit Debug D</u>esktop <u>Window H</u>elp 🌯 🍓 📁 💭 💦 👫 🍓 🧕 Columns visible: 4 ↓ ↑ ▼ ... C:\Work\comp\engthofline2.m · ... C:\Work\comp\engthofline.m lengthofline2.m lengthofline.m C:\Work\comp C:\Work\comp 12-Nov-2009 16:56:52 12-Nov-2009 16:55:35 9 differences found. Use the toolbar buttons to navigate to them. 1 function [len,dims] = lengthofline2(hlin x function [len,dims] = lengthofline(hline 2 $\overline{2}$ %LENGTHOFLINE Calculates the length of a . %LENGTHOFLINE Calculates the length of a 3 % LEN = LENGTHOFLINE(HLINE) takes the . % LEN = LENGTHOFLINE(HLINE) takes the 3 4 % input, and returns its length. The . % input, and returns its length. The 4 5 % dependent on the number of distinct . % dependent on the number of distinct 5 . % 6 % 6 [LEN,DIM] = LENGTHOFLINE(HLINE) addi . % [LEN,DIM] = LENGTHOFLINE(HLINE) addi 2D or 3D by returning either a numer . % 2D or 3D by returning either a numer 7 % 7 8 % 8 9 % plane parallel to a coordinate plane . % plane parallel to a coordinate plane 9 10 % 10 11 % If HLINE is a matrix of line handles . % If HLINE is a matrix of line handles 11 12 % . % 12 13 % Example: . % Example: 13 figure; h2 = plot3(1:10, rand(1,1 . % figure; h2 = plot3(1:10, rand(1, 1 14 % 14 hold on; h1 = plot(1:10, rand(10, . % hold on; h1 = plot(1:10, rand(10, 15 15 % [len,dim] = lengthofline([h1 h2] . % [len,dim] = lengthofline([h1 h2] 16 16 % 17 17 18 % 18 Copyright 1984-2005 The MathWorks, I x % Copyright 1984-2004 The MathWorks, I \$Revision: 1.1.6.6 \$ \$Date: 2007/01 x \$ \$Revision: 1.1.6.5 \$ \$Date: 2006/08 19 % 19 20 20 21 % Find input indices that are not line o . % Find input indices that are not line o 21 22 nothandle = ~ishandle(hline); . nothandle = ~ishandle(hline); 22 23 notline = false(size(hline)); < 24 for nh = 1:numel(hline) x for nh = 1:prod(size(hline)) 23 ----curvefit vs. curvefit × curvefit × File Comparison: 1 × Folder Comparison: 1 × Iengthofine2.m vs. lengthofine.m ×

'techdoc','matlab env','examples','lengthofline2.m'))

For information about using the report features, see "Comparing Text Files".

Note If the text files you compare are XML files, you see different results if you have MATLAB[®] Report Generator[™] installed. For details, see "Comparing Files and Folders".

Compare Two MAT-Files

To compare two example files:

visdiff(fullfile(matlabroot,'toolbox','matlab','demos','gatlin.mat'), ...
fullfile(matlabroot,'toolbox','matlab','demos','gatlin2.mat'))

A File and Folder Comparison	s - C:\ox\matlab\demos\gat		
<u>File Edit Debug D</u> esktop <u>W</u>		X 5 K	
🌯 🐂 🖆 💭 👪 🖊		880	
:\matlab\demos\gatlin.mat 🔻	matlab\demos\gatlin2.mat		
File Comparison - gatlin.mat vs. gatlin2.mat			
Variables which appear in both files but have different values			
are shown in red.			
Click on a variable name to see its contents in the Variable			
Editor.			
Variables in gatlin.mat	Variables in gatlin2.mat		
X	X		
 caption			
	map		
Load gatlin.mat			
Load gatlin2.mat			
		•	
		11.	


For information about the report features, see "Comparing MAT-Files".

Compare Two Binary Files

The following example code adds a folder containing two MEX-files to the MATLAB path, and then compares the files:

```
addpath([matlabroot '\extern\examples\shrlib'])
visdiff('shrlibsample.mexw32', 'yprime.mexw32')
```

The File and Folder Comparisons tool opens and indicates that the files are different, but does not provide details about the differences.




Compare Two Folders


To view an example folder comparison and instructions for using the report features, see "Comparing Folders".

- **Alternatives** As an alternative to the visdiff function, compare files and folders using any of these GUI methods:
 - From the Current Folder browser:

- Select a file or folder. Right-click the file or folder, and select Compare Against.
- For two files or subfolders in the same folder, select the files or folders. Then, right-click, and select Compare Selected Files or Compare Selected Folders.
- From the MATLAB desktop, select **Desktop** > **File and Folder Comparisons**, and then select the files or folders to compare.
- If you have a file open in the Editor, select **Tools > Compare Against**. You can use the Editor options browse, **Autosave Version**, or **Compare Against Version on Disk**.
- **How To** "Comparing Files and Folders"

Purpose	Coordinate and color limits for volume data
Syntax	<pre>lims = volumebounds(X,Y,Z,V) lims = volumebounds(X,Y,Z,U,V,W) lims = volumebounds(V), lims = volumebounds(U,V,W)</pre>
Description	<pre>lims = volumebounds(X,Y,Z,V) returns the x, y, z, and color limits of the current axes for scalar data. lims is returned as a vector:</pre>
	[xmin xmax ymin ymax zmin zmax cmin cmax]
	You can pass this vector to the axis command.
	<pre>lims = volumebounds(X,Y,Z,U,V,W) returns the x, y, and z limits of the current axes for vector data. lims is returned as a vector:</pre>
	[xmin xmax ymin ymax zmin zmax]
	lims = volumebounds(V), lims = volumebounds(U,V,W) assumes X, Y, and Z are determined by the expression
	[X Y Z] = meshgrid(1:n,1:m,1:p)
	where [m n p] = size(V).
Examples	This example uses volumebounds to set the axis and color limits for an isosurface generated by the flow function.
	<pre>[x y z v] = flow; p = patch(isosurface(x,y,z,v,-3)); isonormals(x,y,z,v,p) daspect([1 1 1]) isocolors(x,y,z,flipdim(v,2),p) shading interp axis(volumebounds(x,y,z,v)) view(3) camlight lighting phong</pre>





Purpose	Voronoi diagram
Syntax	<pre>voronoi(x,y) voronoi(x,y,TRI) voronoi(dt) voronoi(AX,) voronoi(,'LineSpec') h = voronoi() [vx,vy] = voronoi()</pre>
Description	<pre>voronoi(x,y) plots the bounded cells of the Voronoi diagram for the points x,y. Lines-to-infinity are approximated with an arbitrarily distant endpoint.</pre>
	voronoi(x,y,TRI) uses the triangulation TRI instead of computing it via delaunay.
	<code>voronoi(dt)</code> uses the Delaunay triangulation dt instead of computing it.
	voronoi(AX,) plots into AX instead of gca.
	voronoi(, 'LineSpec') plots the diagram with color and line style specified.
	h = voronoi() returns, in h, handles to the line objects created.
	<pre>[vx,vy] = voronoi() returns the finite vertices of the Voronoi edges in vx and vy so that plot(vx,vy,'-',x,y,'.') creates the Voronoi diagram. The lines-to-infinity are the last columns of vx and vy. To ensure the lines-to-infinity do not affect the settings of the axis limits, use the commands:</pre>
	h = plot(VX,VY,'-',X,Y,'.'); set(h(1:end-1),'xliminclude','off','yliminclude','off')

Note For the topology of the Voronoi diagram, i.e., the vertices for each Voronoi cell, use voronoin.

[v,c] = voronoin([x(:) y(:)])

voronoi(X,Y,options) specifies a cell array of strings that were previously used by Qhull. Qhull-specific options are no longer required and are currently ignored. Support for these options will be removed in a future release.

convhull uses CGAL, see http://www.cgal.org.

Definition Consider a set of coplanar points p. For each point P_x in the set p, you can draw a boundary enclosing all the intermediate points lying closer to P_x than to other points in the set p. Such a boundary is called a *Voronoi polygon*, and the set of all Voronoi polygons for a given point set is called a *Voronoi diagram*.

Visualization Use one of these methods to plot a Voronoi diagram:


- If you provide no output argument, voronoi plots the diagram. See Example 1.
- To gain more control over color, line style, and other figure properties, use the syntax [vx,vy] = voronoi(...). This syntax returns the vertices of the finite Voronoi edges, which you can then plot with the plot function. See Example 2.
- To fill the cells with color, use voronoin with n = 2 to get the indices of each cell, and then use patch and other plot functions to generate the figure. Note that patch does not fill unbounded cells with color. See Example 3.

Examples

Example 1

This code uses the voronoi function to plot the Voronoi diagram for 10 randomly generated points.

```
x = gallery('uniformdata',[1 10],0);
y = gallery('uniformdata',[1 10],1);
voronoi(x,y)
```




Example 2

This code uses the vertices of the finite Voronoi edges to plot the Voronoi diagram for the same 10 points.

```
x = gallery('uniformdata',[1 10],0);
y = gallery('uniformdata',[1 10],1);
[vx, vy] = voronoi(x,y);
plot(x,y,'r+',vx,vy,'b-'); axis equal
```

voronoi




Note that you can add this code to get the figure shown in Example 1.

xlim([min(x) max(x)])
ylim([min(y) max(y)])

Example 3

This code uses voronoin and patch to fill the bounded cells of the same Voronoi diagram with color.



See Also DelaunayTri, convhull, delaunay, LineSpec, plot, voronoin

DelaunayTri.voronoiDiagram

Purpose	Voronoi diagram		
Syntax	[V, R] = voronoiDiagram(DT)		
Description	[V, R] = voronoiDiagram(DT) returns the vertices V and regions R of the Voronoi diagram of the points DT.X. The region R{i} is a cell array of indices into V that represents the Voronoi vertices bounding the region. The Voronoi region associated with the i'th point, DT.X(i) is R{i}. For 2-D, vertices in R{i} are listed in adjacent order, i.e. connecting them will generate a closed polygon (Voronoi diagram). For 3-D the vertices in R{i} are listed in ascending order.		
	The Voronoi regions associated with points that lie on the convex hull of DT.X are unbounded. Bounding edges of these regions radiate to infinity. The vertex at infinity is represented by the first vertex in V.		
Input Arguments	DT	Delaunay triangulation.	
Output Arguments	V	numv-by-ndim matrix representing the coordinates of the Voronoi vertices, where numv is the number of vertices and ndim is the dimension of the space where the points reside.	
	R	Vector cell array of length(DR.X), representing the Voronoi cell associated with each point.	
Definitions	around each point X(i) the region are closer to	of a discrete set of points X decomposes the space into a region of influence R{i}. Locations within point i than any other point. The region of Voronoi region. The collection of all the Voronoi diagram.	

The *convex hull* of a set of points X is the smallest convex polygon (or polyhedron in higher dimensions) containing all of the points of X.

Examples Compute the Voronoi Diagram of a set of points:

	X = [0.5]	0
	0	0.5
	-0.5	-0.5
	-0.2	-0.1
	-0.1	0.1
	0.1	-0.1
	0.1	0.1]
	dt = Delau	nayTri(X)
	[V,R] = vo	ronoiDiagram(dt)
c a		
See Also	voronoi	
	voronoin	

voronoin

Purpose	N-D Voronoi diagram		
Syntax	<pre>[V,C] = voronoin(X) [V,C] = voronoin(X,options)</pre>		
Description	[V,C] = voronoin(X) returns Voronoi vertices V and the Voronoi cells C of the Voronoi diagram of X. V is a numv-by-n array of the numv Voronoi vertices in n-dimensional space, each row corresponds to a Voronoi vertex. C is a vector cell array where each element contains the indices into V of the vertices of the corresponding Voronoi cell. X is an m-by-n array, representing m n-dimensional points, where n > 1 and m >= n+1.		
	The first row of V is a point at infinity. If any index in a cell of the cell array is 1, then the corresponding Voronoi cell contains the first point in V, a point at infinity. This means the Voronoi cell is unbounded.		
	voronoin uses Qhull.		
	<pre>[V,C] = voronoin(X,options) specifies a cell array of strings options to be used in Qhull. The default options are</pre>		
	• { 'Qbb ' } for 2- and 3-dimensional input		
	• {'Qbb','Qx'} for 4 and higher-dimensional input		
	If options is [], the default options are used. If code is { ' ' }, no options are used, not even the default. For more information on Qhull and its options, see http://www.qhull.org.		
Visualization	You can plot individual bounded cells of an n-dimensional Voronoi diagram. To do this, use convhulln to compute the vertices of the facets that make up the Voronoi cell. Then use patch and other plot functions to generate the figure.		
Examples	Example 1		
	Let		
	x = [0.5 0		

0.5	
-0.5	
-0.1	
0.1	
-0.1	
0.1]
	-0.5 -0.1 0.1 -0.1

then

[V,C] = voronoin(x)

```
V =
```

v		
	Inf	Inf
	0.3833	0.3833
	0.7000	-1.6500
	0.2875	0.0000
	-0.0000	0.2875
	-0.0000	-0.0000
	-0.0500	-0.5250
	-0.0500	-0.0500
	-1.7500	0.7500
	-1.4500	0.6500
C =		

[1x4	double]
[1x5	double]
[1x4	double]
[1x4	double]
[1x4	double]
[1x5	double]
[1x4	double]

Use a for loop to see the contents of the cell array ${\tt C}.$

9	1	3	7	
10	8	7	9	
10	5	6	8	
8	6	4	3	7
6	4	2	5	

In particular, the fifth Voronoi cell consists of 4 points: V(10,:), V(5,:), V(6,:), V(8,:).

Example 2

The following example illustrates the options input to voronoin. The commands

X = [-1 -1; 1 -1; 1 1; -1 1]; [V,C] = voronoin(X)

return an error message.

```
? qhull input error: can not scale last coordinate. Input is cocircular
```

or cospherical. Use option 'Qz' to add a point at infinity.

The error message indicates that you should add the option 'Qz'. The following command passes the option 'Qz', along with the default 'Qbb', to voronoin.

```
[V,C] = voronoin(X,{'Qbb','Qz'})
V =
Inf Inf
0 0
C =
[1x2 double]
[1x2 double]
[1x2 double]
[1x2 double]
```

[1x2 double]

Algorithm	<pre>voronoin is based on Qhull [1]. For information about Qhull, see http://www.qhull.org/. For copyright information, see http://www.qhull.org/COPYING.txt.</pre>
See Also	DelaunayTri, convhull, convhulln, delaunay, delaunayn, voronoi
Reference	[1] Barber, C. B., D.P. Dobkin, and H.T. Huhdanpaa, "The Quickhull Algorithm for Convex Hulls," <i>ACM Transactions on Mathematical</i> <i>Software</i> , Vol. 22, No. 4, Dec. 1996, p. 469-483.

wait

Purpose	Wait until timer stops running
Syntax	wait(obj)
Description	<pre>wait(obj) blocks the MATLAB command line and waits until the timer, represented by the timer object obj, stops running. When a timer stops running, the value of the timer object's Running property changes from 'on' to 'off'.</pre>
	If obj is an array of timer objects, wait blocks the MATLAB command line until all the timers have stopped running.
	If the timer is not running, wait returns immediately.
See Also	timer, start, stop

Purpose	Open or update a wait bar dialog box
Syntax	<pre>h = waitbar(x,'message') waitbar(x,'message','CreateCancelBtn','button_callback') waitbar(x,'message',property_name,property_value,) waitbar(x) waitbar(x,h) waitbar(x,h,'updated message')</pre>
Description	A wait bar is a figure that displays what percentage of a calculation is complete as the calculation proceeds by progressively filling a bar with red from left to right. h = waitbar(x, 'message') displays a wait bar of fractional length x. The wait bar figure displays until the code that controls it closes it or the use clicks its Close Window button. Its (figure) handle is returned in h. The argument x must be between 0 and 1.
	<pre>Note Wait bars are not modal figures (their WindowStyle is 'normal'). They often appear to be modal because the computational loops within which they are called prevent interaction with the Command Window until they terminate. For more information, see WindowStyle in the MATLAB Figure Properties documentation. waitbar(x,'message','CreateCancelBtn','button_callback') specifying CreateCancelBtn adds a Cancel button to the figure that executes the MATLAB commands specified in button_callback when the user clicks the Cancel button or the Close Figure button. waitbar sets both the Cancel button callback and the figure CloseRequestFcn to the string specified in button_callback. waitbar(x,'message',property_name,property_value,) optional arguments property_name and property_value enable you to set figure properties for the waitbar.</pre>

waitbar(x) subsequent calls to waitbar(x) extend the length of the bar to the new position x. Successive values of x normally increase. If they decrease, the wait bar runs in reverse.

waitbar(x,h) extends the length of the bar in the wait bar h to the new position x.

waitbar(x,h, 'updated message') updates the message text in the waitbar figure, in addition to setting the fractional length to x.

Examples Example 1 – Basic Wait Bar

Typically, you call waitbar repeatedly inside a for loop that performs a lengthy computation. For example:

```
h = waitbar(0, 'Please wait...');
steps = 1000;
for step = 1:steps
    % computations take place here
    waitbar(step / steps)
end
close(h)
```



Example 2 – Wait Bar with Dynamic Text and Cancel Button

Adding a **Cancel** button allows user to abort the computation. Clicking it sets a logical flag in the figure's application data (appdata). The function tests for that value within the main loop and exits the loop as soon as the flag has been set. The example iteratively approximates the value of π . At each step, the current value is encoded as a string and displayed in the wait bar's message field. When the function finishes,

it destroys the wait bar and returns the current estimate of π and the number of steps it ran.


Copy the following function to a code file and save it as approxpi.m. Execute it as follows, allowing it to run for 10,000 iterations.

```
[estimated_pi steps] = approxpi(10000)
```

You can click **Cancel** or close the window to abort the computation and return the current estimate of π .

```
function [valueofpi step] = approxpi(steps)
% Converge on pi in steps iterations, displaying waitbar.
% User can click Cancel or close button to exit the loop.
% Ten thousand steps yields error of about 0.001 percent.
h = waitbar(0,'1','Name','Approximating pi...',...
            'CreateCancelBtn',...
            'setappdata(gcbf,''canceling'',1)');
setappdata(h, 'canceling',0)
% Approximate as pi^2/8 = 1 + 1/9 + 1/25 + 1/49 + ...
pisgover8 = 1;
denom = 3;
valueofpi = sqrt(8 * pisqover8);
for step = 1:steps
    % Check for Cancel button press
    if getappdata(h, 'canceling')
        break
    end
    % Report current estimate in the waitbar's message field
    waitbar(step/steps,h,sprintf('%12.9f',valueofpi))
    % Update the estimate
    pisqover8 = pisqover8 + 1 / (denom * denom);
    denom = denom + 2;
    valueofpi = sqrt(8 * pisqover8);
end
delete(h)
                % DELETE the waitbar; don't try to CLOSE it.
```

The function sets the figure Name property to describe what is being computed. In the for loop, calling waitbar sets the fractional progress indicator and displays intermediate results. the code waitbar(i/steps,h,sprintf('%12.9f',valueofpi)) sets the wait bar's message variable to a string representation of the current estimate of *pi*. Naturally, the extra computation involved makes iterations last longer than they need to, but such feedback can be helpful to users.



Note You should call delete to remove a wait bar when you give it a CloseRequestFcn, as in the preceding code; calling close does not close it, and makes its Cancel and Close Window buttons unresponsive. This happens because the figure's CloseRequestFcn recursively calls itself. In such a situation you must forcibly remove the wait bar, for example like this:

```
set(0,'ShowHiddenHandles','on')
delete(get(0,'Children'))
```

However, as issuing these commands will delete all open figures—not just the wait bar—it is best never to use close in a CloseRequestFcn to close a window.

See Also "Predefined Dialog Boxes" on page 1-113 for related functions close, delete, dialog, msgbox, getappdata, setappdata

Purpose	Wait for condition before resuming execution
Syntax	waitfor(h) waitfor(h,'PropertyName') waitfor(h,'PropertyName',PropertyValue)
Description	<pre>waitfor(h) blocks the caller execution stream until the graphics object identified by handle h is deleted or you type Ctrl+C in the Command Window. h must be scalar. When either of those events occur, waitfor stops blocking execution and returns. If h does not exist, waitfor returns immediately without processing any events.</pre>
	<pre>waitfor(h, 'PropertyName'), in addition to the conditions in the previous syntax, stops blocking and returns when the value of 'PropertyName' (any property of the graphics object h) changes. If 'PropertyName' is not a valid property for the object, waitfor returns immediately without processing any events.</pre>
	waitfor(h, 'PropertyName', PropertyValue) stops blocking and returns when the value of 'PropertyName' for the graphics object h changes to PropertyValue. If you previously set 'PropertyName' to PropertyValue, waitfor returns immediately without processing any events.
Definitions	waitfor blocks the caller execution stream so that command-line expressions and statements in the blocked file do not execute until a specified condition occurs. While waitfor blocks an execution stream, other execution streams generated by callbacks that respond to various events (for example, pressing a mouse button) can run, unaffected by waitfor. It also blocks Simulink models from executing. However, callbacks do execute during the blocking of the execution stream. waitfor can block nested execution streams. For example, a callback invoked during a waitfor statement can invoke waitfor.
Examples	Create a plot and pause execution of the rest of the statements until you delete the figure window:

```
h = figure;
plot(rand(10,1));
disp('Waiting for you to delete the figure...')
drawnow % Necessary to plot and put message on the screen
waitfor(h)
% The next line only executes when the figure is deleted
disp('Thank you.')
```

Display the current date and time only while a button is depressed

```
figure('Position',[560 526 420 315]);
hb = uicontrol('Style', 'togglebutton', 'Value', 0, ...
               'Units', 'normalized',...
               'Position',[.4 .6 .2 .05],...
               'String','Start/Stop');
ht = uicontrol('Style', 'text', 'Units', 'normalized',...
               'Position',[.275 .5 .425 .04],...
               'FontSize',10,...
               'String',datestr(now));
% Iterate 100,000 times then quit
% Typing Ctrl+C in Command Window will also stop the count
count = 0;
while count < 100000
                            % Exit condition
    waitfor(hb,'Value',1) %Until togglebutton is down
    % Text only updates while Start/Stop button is down
    set(ht,'String',datestr(now)) % Update date and time
    drawnow
                            % Update text field
    count = count+1;
end
```

Start/Stop	
17-Apr-2009 11:01:03	

If you close the figure while the code is executing, an error occurs because the code attempts to access handles of objects that no longer exist. You can handle the error by enclosing code in the loop in a try/catch block, as follows:

```
while count < 10000 % Exit condition
    try % An error occurs if you delete the figure here
    waitfor(hb,'Value',1) %Until togglebutton is down
    % Text only updates while Start/Stop button is down
    set(ht,'String',datestr(now)) % Update date and time
    drawnow % Update text field
    catch ME % Catch the error and exit gracefully
    % You can place more code to respond to the error here
    return
    end
end</pre>
```

waitfor

	The ME variable is a MATLAB Exception object that you can use to determine the type of error that occurred. For more information, see "Responding to an Exception".
See Also	drawnow keyboard pause uiresume uiwait waitforbuttonpress
How To	 "Controlling Callback Execution and Interruption" Developing User Interfaces

Purpose	Wait for key press or mouse-button click
Syntax	k = waitforbuttonpress
Description	<pre>k = waitforbuttonpress blocks the caller's execution stream until the function detects that the user has clicked a mouse button or pressed a key while the figure window is active. The function returns</pre>
	• 0 if it detects a mouse button click
	• 1 if it detects a key press
	Additional information about the event that causes execution to resume is available through the figure's CurrentCharacter, SelectionType, and CurrentPoint properties.
	If a WindowButtonDownFcn is defined for the figure, its callback is executed before waitforbuttonpress returns a value.
	You can interrupt waitforbuttonpress by typing $Ctrl+C$, but an error results unless the function is called from within a try-catch block. You also receive an error from waitforbuttonpress if you close the figure by clicking the X close box unless you call waitforbuttonpress within a try-catch block.
Example	These statements display text in the Command Window when the user either clicks a mouse button or types a key in the figure window:
	<pre>w = waitforbuttonpress; if w == 0 disp('Button click') else disp('Key press') end</pre>
See Also	dragrect, ginput, rbbox, waitfor
	"User Interface Development" on page 1-114 for related functions

warndlg

Purpose	Open warning dialog box
Syntax	<pre>h = warndlg h = warndlg(warningstring) h = warndlg(warningstring,dlgname) h = warndlg(warningstring,dlgname,createmode)</pre>
Description	h = warndlg displays a dialog box named Warning Dialog containing the string This is the default warning string. The warndlg function returns the handle of the dialog box in h. The warning dialog box disappears after the user clicks OK .
	 h = warndlg(warningstring) displays a dialog box with the title Warning Dialog containing the string specified by warningstring. The warningstring argument can be any valid string format - cell arrays are preferred.
	To use multiple lines in your warning, define warningstring using either of the following:
	• sprintf with newline characters separating the lines
	warndlg(sprintf('Message line 1 \n Message line 2'))
	• Cell arrays of strings
	<pre>warndlg({'Message line 1';'Message line 2'})</pre>
	h = warndlg(warningstring,dlgname) displays a dialog box with title dlgname.
	h = warndlg(warningstring,dlgname, <i>createmode</i>) specifies whether the warning dialog box is modal or nonmodal. Optionally, it can also specify an interpreter for warningstring and dlgname. The <i>createmode</i> argument can be a string or a structure.
	If <i>createmode</i> is a string, it must be one of the values shown in the following table.

createmode Value	Description
modal	Replaces the warning dialog box having the specified Title, that was last created or clicked on, with a modal warning dialog box as specified. All other warning dialog boxes with the same title are deleted. The dialog box which is replaced can be either modal or nonmodal.
non-modal (default)	Creates a new nonmodal warning dialog box with the specified parameters. Existing warning dialog boxes with the same title are not deleted.
replace	Replaces the warning dialog box having the specified Title, that was last created or clicked on, with a nonmodal warning dialog box as specified. All other warning dialog boxes with the same title are deleted. The dialog box which is replaced can be either modal or nonmodal.

Note A modal dialog box prevents the user from interacting with other windows before responding. To block MATLAB program execution as well, use the uiwait function.

If you open a dialog with errordlg, msgbox, or warndlg using 'CreateMode', 'modal' and a non-modal dialog created with any of these functions is already present and *has the same name as the modal dialog*, the non-modal dialog closes when the modal one opens.

For more information about modal dialog boxes, see WindowStyle in the Figure Properties.

warndlg

If CreateMode is a structure, it can have fields WindowStyle and Interpreter. WindowStyle must be one of the options shown in the table above. Interpreter is one of the strings 'tex' or 'none'. The default value for Interpreter is 'none'.

Examples The statement

warndlg('Pressing OK will clear memory','!! Warning !!')

displays this dialog box:



See Also dialog, errordlg, helpdlg, inputdlg, listdlg, msgbox, questdlg figure, uiwait, uiresume, warning "Predefined Dialog Boxes" on page 1-113 for related functions

Purpose	Warning message
Syntax	<pre>warning('message') warning('message', a1, a2,) warning('message_id', 'message') warning('message_id', 'message', a1, a2,, an) s = warning(state, 'message_id') s = warning(state, mode)</pre>
Description	warning('message') displays descriptive text message and sets the warning state that lastwarn returns. If message is an empty string (''), warning resets the warning state but does not display any text.
	warning('message', a1, a2,) displays a message string that contains formatting conversion characters, such as those used with the MATLAB sprintf function. Each conversion character in message is converted to one of the values a1, a2, in the argument list.
	Note MATLAB converts special characters (like \n and %d) in the warning message string only when you specify more than one input argument with warning. See Example 4 below.
	warning('message_id', 'message') attaches a unique identifier, or message_id, to the warning message. The identifier enables you to single out certain warnings during the execution of your program, controlling what happens when the warnings are encountered. See "Message Identifiers" and "Warning Control" in the MATLAB Programming Fundamentals documentation for more information on the message_id argument and how to use it.
	warning('message_id', 'message', a1, a2,, an) includes formatting conversion characters in message, and the character translations in arguments a1, a2,, an.
	s = warning(state, 'message_id') is a warning control statement that enables you to indicate how you want MATLAB to act on certain

warnings. The state argument can be 'on', 'off', or 'query'. The message_id argument can be a message identifier string, 'all', or 'last'. See "Warning Control Statements" in the MATLAB Programming Fundamentals documentation for more information.

Output s is a structure array that indicates the previous state of the selected warnings. The structure has the fields identifier and state. See "Output from Control Statements" in the MATLAB Programming Fundamentals documentation for more.

s = warning(state, mode) is a warning control statement that enables you to display a stack trace or display more information with each warning. The state argument can be 'on', 'off', or 'query'. The mode argument can be 'backtrace' or 'verbose'. See "Backtrace and Verbose Modes" in the MATLAB Programming Fundamentals documentation for more information.

Examples Example 1

Generate a warning that displays a simple string:

```
if ~ischar(p1)
    warning('Input must be a string')
end
```

Example 2

Generate a warning string that is defined at run-time. The first argument defines a message identifier for this warning:

```
warning('MATLAB:paramAmbiguous', ...
'Ambiguous parameter name, "%s".', param)
```

Example 3

Attempting to concatenate integers of a different size generates the following warning:

```
warning on all;
A = [int8(150), int16(300)];
```

Warning: Concatenation with dominant (left-most) integer class may overflow other operands on conversion to return class.

If your program displays additional warning messages but you would prefer to see only this one, you can set the state of all warnings to off, and then set this one warning to on. To set the warning state, you must first know the message identifier for the one warning you want to enable. Query the last warning to acquire the identifier:

```
warnStruct = warning('query', 'last');
msgid_integerCat = warnStruct.identifier
msgid_integerCat =
MATLAB:concatenation:integerInteraction
```

Disable all but the integer concatenation warning:

warning off all; warning('on', msgid_integerCat);

Use query to determine the current state of all warnings. It reports that you have set all warnings to off with the exception of Simulink:actionNotTaken:

```
The default warning state is 'off'. Warnings not set to the default are
State Warning Identifier
on MATLAB:concatenation:integerInteraction
```

Example 4

MATLAB converts special characters (like \n and %d) in the warning message string only when you specify more than one input argument with warning. In the single argument case shown below, \n is taken to mean backslash-n. It is not converted to a newline character:

warning('In this case, the newline \n is not converted.')
Warning: In this case, the newline \n is not converted.

But, when more than one argument is specified, MATLAB does convert special characters. This is true regardless of whether the additional argument supplies conversion values or is a message identifier:

Example 5

Turn on one particular warning, saving the previous state of this one warning in **s**. Remember that this nonquery syntax performs an implicit query prior to setting the new state:

s = warning('on', 'Control:parameterNotSymmetric');

After doing some work that includes making changes to the state of some warnings, restore the original state of all warnings:

warning(s)


See Also lastwarn, warndlg, error, lasterror, errordlg, dbstop, disp, sprintf

PurposeWaterfall plot



GUI Alternatives	To graph selected variables, use the Plot Selector in the Workspace Browser, or use the Figure Palette Plot Catalog. Manipulate graphs in <i>plot edit</i> mode with the Property Editor. For details, see Plotting Tools — Interactive Plotting in the MATLAB Graphics documentation and Creating Graphics from the Workspace Browser in the MATLAB Desktop Tools documentation.
Syntax	<pre>waterfall(Z) waterfall(X,Y,Z) waterfall(,C) waterfall(axes_handles,) h = waterfall()</pre>
Description	The waterfall function draws a mesh similar to the meshz function, but it does not generate lines from the columns of the matrices. This produces a "waterfall" effect. waterfall(Z) creates a waterfall plot using $x = 1:size(Z,1)$ and y = 1:size(Z,1). Z determines the color, so color is proportional to surface height.
	waterfall(X,Y,Z) creates a waterfall plot using the values specified in X, Y, and Z. Z also determines the color, so color is proportional to the surface height. If X and Y are vectors, X corresponds to the columns of Z, and Y corresponds to the rows, where length(x) = n, length(y) = m, and $[m,n] = size(Z)$. X and Y are vectors or matrices that define the x- and y-coordinates of the plot. Z is a matrix that defines the z-coordinates of the plot (i.e., height above a plane). If C is omitted, color is proportional to Z.
	waterfall(,C) uses scaled color values to obtain colors from the current colormap. Color scaling is determined by the range of C, which

	must be the same size as Z. MATLAB performs a linear transformation on C to obtain colors from the current colormap.
	waterfall(axes_handles,) plots into the axes with handle axes_handle instead of the current axes (gca).
	h = waterfall() returns the handle of the patch graphics object used to draw the plot.
Remarks	For column-oriented data analysis, use waterfall(Z') or waterfall(X',Y',Z').
Examples	Produce a waterfall plot of the peaks function.
	[X,Y,Z] = peaks(30); waterfall(X,Y,Z)



Algorithm The range of X, Y, and Z, or the current setting of the axes Llim, YLim, and ZLim properties, determines the range of the axes (also set by axis). The range of C, or the current setting of the axes CLim property, determines the color scaling (also set by caxis).

The CData property for the patch graphics objects specifies the color at every point along the edge of the patch, which determines the color of the lines.

The waterfall plot looks like a mesh surface; however, it is a patch graphics object. To create a surface plot similar to waterfall, use the meshz function and set the MeshStyle property of the surface to 'Row'.

For a discussion of parametric surfaces and related color properties, see surf.

See Also axes, axis, caxis, meshz, ribbon, surf

Properties for patch graphics objects

Purpose	Information about WAVE (.wav) sound file
Syntax	<pre>[m d] = wavfinfo(filename)</pre>
Description	<pre>[m d] = wavfinfo(filename) returns information about the contents of the WAVE sound file specified by the string filename. Enclose the filename input in single quotes.</pre>
	<i>m</i> is the string 'Sound (WAV) file', if <i>filename</i> is a WAVE file. Otherwise, it contains an empty string ('').
	<i>d</i> is a string that reports the number of samples in the file and the number of channels of audio data. If <i>filename</i> is not a WAVE file, it contains the string 'Not a WAVE file'.
See Also	wavplay, wavread, wavrecord, wavwrite

wavplay

Purpose	Play recorded sound on PC-based audio output device
Syntax	wavplay(y,Fs) wavplay(, <i>mode</i> ')
Description	<pre>wavplay(y,Fs) plays the audio signal stored in the vector y on a PC-based audio output device. Fs is the integer sample rate in Hz (samples per second). The default value for Fs is 11025 Hz. wavplay supports only 1- or 2-channel (mono or stereo) audio signals. To play in stereo, y must be a two-column matrix.</pre>
	<pre>wavplay(, mode') specifies how wavplay interacts with the command line, according to the string 'mode'. The string 'mode' can be</pre>
	• 'async': You have immediate access to the command line as soon as the sound begins to play on the audio output device (a nonblocking device call).

• 'sync' (default value): You don't have access to the command line until the sound has finished playing (a blocking device call).

The audio signal y can be one of four data types. The number of bits used to quantize and play back each sample depends on the data type.

Data Types for wavplay

Data Type	Quantization
Double-precision (default value)	16 bits/sample
Single-precision	16 bits/sample
16-bit signed integer	16 bits/sample
8-bit unsigned integer	8 bits/sample

Remarks	The wavplay function is for use only with 32-bit Microsoft Windows operating systems. To play audio data on other platforms, use audioplayer.
Examples	The MAT-files gong.mat and chirp.mat both contain an audio signal y and a sampling frequency Fs. Load and play the gong and the chirp audio signals. Change the names of these signals in between load commands and play them sequentially using the 'sync' option for wavplay.
	<pre>load chirp; y1 = y; Fs1 = Fs; load gong; wavplay(y1,Fs1,'sync') % The chirp signal finishes before the wavplay(y,Fs) % gong signal begins playing.</pre>
See Also	audioplayer, wavfinfo, wavread, wavrecord, wavwrite

wavread

Purpose	Read WAVE (.wav) sound file
Graphical Interface	As an alternative to wavread, use the Import Wizard. To activate the Import Wizard, select File > Import Data .
Syntax	<pre>y = wavread(filename) [y, Fs] = wavread(filename) [y, Fs, nbits] = wavread(filename) [y, Fs, nbits, opts] = wavread(filename) [] = wavread(filename, N) [] = wavread(filename, [N1 N2]) [] = wavread(, fmt) siz = wavread(filename,'size')</pre>
Description	<pre>y = wavread(filename) loads a WAVE file specified by the string filename, returning the sampled data in y. If filename does not include an extension, wavread appends .wav. [y, Fs] = wavread(filename) returns the sample rate (Fs) in Hertz used to encode the data in the file. [y, Fs, nbits] = wavread(filename) returns the number of bits per sample (nbits). [y, Fs, nbits, opts] = wavread(filename) returns a structure</pre>
	<pre>opts of additional information contained in the WAV file. The content of this structure differs from file to file. Typical structure fields include opts.fmt (audio format information) and opts.info (text that describes the title, author, etc.). [] = wavread(filename, N) returns only the first N samples</pre>
	from each channel in the file.
	[] = wavread(<i>filename</i> , [<i>N1 N2</i>]) returns only samples <i>N1</i> through <i>N2</i> from each channel in the file.
	[] = wavread(, fmt) specifies the data format of y used to represent samples read from the file. fmt can be either of the following values, or a partial match (case-insensitive):

double'	Double-precision normalized samples (default).
native'	Samples in the native data type found in the file

siz = wavread(filename, 'size') returns the size of the audio data
contained in filename instead of the actual audio data, returning the
vector siz = [samples channels].

Output Scaling

'

The range of values in y depends on the data format *fmt* specified. Some examples of output scaling based on typical bit-widths found in a WAV file are given below for both 'double' and 'native' formats.

Native Formats

Number of Bits	MATLAB Data Type	Data Range
8	uint8 (unsigned integer)	0 <= y <= 255
16	int16 (signed integer)	-32768 <= y <= +32767
24	int32 (signed integer)	-2^23 <= y <= 2^23-1
32	<pre>single (floating point)</pre>	-1.0 <= <i>y</i> < +1.0

Double Formats

Number of Bits	MATLAB Data Type	Data Range
N<32	double	-1.0 <= y < +1.0
N=32	double	-1.0 <= y <= +1.0 Note: Values in y might exceed -1.0 or +1.0 for the case of N=32 bit data samples stored in the WAV file.

wavread

```
wavread supports multi-channel data, with up to 32 bits per sample.
                  wavread supports Pulse-code Modulation (PCM) data format only.
Examples
                  Create a WAV file from the demo file handel.mat, and read portions of
                  the file back into MATLAB.
                     % Create WAV file in current folder.
                     load handel.mat
                     hfile = 'handel.wav';
                     wavwrite(y, Fs, hfile)
                     clear y Fs
                     % Read the data back into MATLAB, and listen to audio.
                     [y, Fs, nbits, readinfo] = wavread(hfile);
                     sound(y, Fs);
                     % Pause before next read and playback operation.
                     duration = numel(y) / Fs;
                     pause(duration + 2)
                     % Read and play only the first 2 seconds.
                     nsamples = 2 * Fs;
                     [y2, Fs] = wavread(hfile, nsamples);
                     sound(y2, Fs);
                     pause(4)
                     % Read and play the middle third of the file.
                     sizeinfo = wavread(hfile, 'size');
                     tot_samples = sizeinfo(1);
                     startpos = tot_samples / 3;
                     endpos = 2 * startpos;
                     [y3, Fs] = wavread(hfile, [startpos endpos]);
                     sound(y3, Fs);
```

See Also audioplayer, audiorecorder, mmfileinfo, sound, wavfinfo, wavwrite

wavrecord

Purpose	Record sound using PC-based audio input device
Syntax	y = wavrecord(n,Fs) y = wavrecord(,ch) y = wavrecord(,' <i>dtype</i> ')
Description	y = wavrecord(n,Fs) records n samples of an audio signal, sampled at a rate of Fs Hz (samples per second). The default value for Fs is 11025 Hz.
	y = wavrecord(,ch) uses ch number of input channels from the audio device. ch can be either 1 or 2, for mono or stereo, respectively. The default value for ch is 1.

y = wavrecord(..., 'dtype') uses the data type specified by the string 'dtype' to record the sound. The following table lists the string values for 'dtype' along with the corresponding bits per sample and acceptable data range for y.

dtype	Bits/sample	y Data Range
'double'	16	−1.0 <= y < +1.0
'single'	16	-1.0 <= y < +1.0
'int16'	16	-32768 <= y <= +32767
'uint8'	8	0 <= y <= 255

Remarks

Standard sampling rates for PC-based audio hardware are 8000, 11025, 22050, and 44100 samples per second. Stereo signals are returned as two-column matrices. The first column of a stereo audio matrix corresponds to the left input channel, while the second column corresponds to the right input channel.

The wavrecord function is for use only with 32-bit Microsoft Windows operating systems. To record audio data from audio input devices on other platforms, use audiorecorder.

Examples	Record 5 seconds of 16-bit audio sampled at 11025 Hz. Play back the recorded sound using wavplay. Speak into your audio device (or produce your audio signal) while the wavrecord command runs.	
	Fs = 11025; y = wavrecord(5*Fs,Fs,'int16'); wavplay(y,Fs);	
See Also	audiorecorder, wavfinfo, wavplay, wavread, wavwrite	

wavwrite

Purpose	Write WAVE (.wav) sound file
Syntax	<pre>wavwrite(y,filename) wavwrite(y,Fs,filename) wavwrite(y,Fs,N,filename)</pre>
Description	<pre>wavwrite(y,filename) writes the data stored in the variable y to a WAVE file called filename. The filename input is a string enclosed in single quotes. The data has a sample rate of 8000 Hz and is assumed to be 16-bit. Each column of the data represents a separate channel. Therefore, stereo data should be specified as a matrix with two columns.</pre>
	wavwrite(y,Fs,filename) writes the data stored in the variable y to a WAVE file called <i>filename</i> . The data has a sample rate of Fs Hz and is assumed to be 16-bit.

wavwrite(y,Fs,N,filename) writes the data stored in the variable y to a WAVE file called *filename*. The data has a sample rate of Fs Hz and is N-bit, where N is 8, 16, 24, or 32.

Input Data Ranges

The range of values in y depends on the number of bits specified by N and the data type of y. The following tables list the valid input ranges based on the value of N and the data type of y.

N Bits	y Data Type	y Data Range	Output Format
8	uint8	0 <= y <= 255	uint8
16	int16	−32768 <= y <= +32767	int16
24	int32	-2^23 <= y <= 2^23 − 1	int32

If *y* contains integer data:

If y	contains	f	loating-p	oint	data:
------	----------	---	-----------	------	-------

N Bits	y Data Type	y Data Range	Output Format
8	single or double	−1.0 <= <i>y</i> < +1.0	uint8
16	single or double	−1.0 <= <i>y</i> < +1.0	int16
24	single or double	−1.0 <= <i>y</i> < +1.0	int32
32	single or double	-1.0 <= y <= +1.0	single

For floating point data where N < 32, amplitude values are clipped to the range $-1.0 \le y \le +1.0$.

Note 8-, 16-, and 24-bit files are type 1 integer pulse code modulation (PCM). 32-bit files are written as type 3 normalized floating point.

See Also

audioplayer, audiorecorder, mmfileinfo, sound, wavfinfo, wavread

Purpose	Open Web site or file in Web or Help browser
Syntax	<pre>web web url web url -new web url -notoolbar web url -noaddressbox web url -helpbrowser web url -browser web() stat = web('url', '-browser') [stat, h1] = web [stat, h1, url] = web</pre>
Description	web opens an empty MATLAB Web browser. web url displays the page specified by url in the MATLAB Web browser. If any MATLAB Web browsers are already open, it displays the page in the browser that was used last. Files up to 1.5 MB in size display in the MATLAB Web browser, while larger files instead display in the system Web browser. The web function accepts a valid URL such as a web site address, a full path to a file, or a relative path to a file (using url within the current folder if it exists there). If url is located in the folder returned when you run docroot (an unsupported utility function), the page displays in the MATLAB Help browser instead of the MATLAB Web browser.
	 web url -new displays the page specified by url in a new MATLAB Web browser. web url -notoolbar displays the page specified by urlin a MATLAB Web browser that does not include the toolbar and address field. If any MATLAB Web browsers are already open, also use the -new option. Otherwise url displays in the browser that was used last, regardless of its toolbar status. web url -noaddressbox displays the page specified by urlin a MATLAB Web browser that does not include the address field. If any MATLAB web browser are already open, also use the -new option. Otherwise url open also use the specified by urlin a MATLAB Web browser that does not include the address field. If any MATLAB web browsers are already open, also use the -new option. Otherwise

url displays in the browser that was used last, regardless of its address field status.

web url **-helpbrowser** displays the page specified by url in the MATLAB Help browser.

web url -browser displays url in a system Web browser window. url can be in any form that the browser supports. On Microsoft Windows and Apple Macintosh platforms, the system Web browser is determined

by the operating system. On UNIX²¹ platforms, the default system Web browser for MATLAB is Mozilla[®] Firefox[®]. To specify a different browser, use MATLAB Web preferences.

 $web(\ldots)$ is the functional form of web.

stat = web('url', '-browser') runs web and returns the status of
web to the variable stat.

Value of stat	Description
0	Browser was found and launched.
1	Browser was not found.
2	Browser was found but could not be launched.

[stat, h1] = web returns the status of web to the variable stat, and returns a handle, h1, to the Sun Microsystems Java class for the last active browser. You can use close(h1) to close the browser instance. The browser, h1, could have been opened by previously executing the web function, or when a desktop tool ran the web function. For example, clicking a link to an external site from the Help browser runs web to open the Web site in a system browser. In that case, h1 would is the handle to that browser instance.

[stat, h1, url] = web returns the status of web to the variable stat, returns a handle to the Java class h1 for the last active browser, and returns its current URL to url.

Examples Display the Mathtools Web site:

web http://www.mathtools.net

MATLAB displays:

21. UNIX is a registered trademark of The Open Group in the United States and other countries.

Toolbar and address field



web http://www.mathworks.com loads the MathWorks Web site home page into the MATLAB Web browser.

web file:///disk/dir1/dir2/foo.html opens the file foo.html in the MATLAB Web browser.

web mydir/myfile.html opens myfile.html in the MATLAB Web browser, where mydir is in the current folder.

web(['file:///' which('foo.html')]) opens foo.html if the file is in a folder on the search path or in the current folder for MATLAB.

web('text://<html><h1>Hello World</h1></html>') displays the
HTML-formatted text Hello World.

web('http://www.mathworks.com', '-new', '-notoolbar') loads the MathWorks Web site home page into a new MATLAB Web browser that does not include a toolbar or address field.

web file:///disk/dir1/foo.html -helpbrowser opens the file foo.html in the MATLAB Help browser. web file:///disk/dir1/foo.html -browser opens the file foo.html in the system Web browser. web mailto:email address uses the system browser's default e-mail application to send a message to email address. web http://www.mathtools.net -browser opens the system Web browser at mathtools.net. [stat,h1]=web('http://www.mathworks.com'); opens mathworks.com in a MATLAB Web browser. Use close(h1) to close the browser window. See Also doc, helpbrowser, matlabcolon, urlread, urlwrite Related topics in the User Guide: • "Using Web Browsers in MATLAB" in the MATLAB Desktop Tools and Development Environment documentation • "Specifying Proxy Server Settings" • "Specifying the System Browser for UNIX Platforms"

Syntax [N, S] = weekday(D) [N, S] = weekday(D, form) [N, S] = weekday(D, locale) [N, S] = weekday(D, form, locale)

Description [N, S] = weekday(D) returns the day of the week in numeric (N) and string (S) form for a given serial date number or date string D. Input argument D can represent more than one date in an array of serial date numbers or a cell array of date strings.

[N, S] = weekday(D, form) returns the day of the week in numeric (N) and string (S) form, where the content of S depends on the form argument. If form is 'long', then S contains the full name of the weekday (e.g., Tuesday). If form is 'short', then S contains an abbreviated name (e.g., Tues) from this table.

The days of the week are assigned these numbers and abbreviations.

Ν	S (short)	S (long)
1	Sun	Sunday
2	Mon	Monday
3	Tue	Tuesday
4	Wed	Wednesday
5	Thu	Thursday
6	Fri	Friday
7	Sat	Saturday

[N, S] = weekday(D, locale) returns the day of the week in numeric (N) and string (S) form, where the format of the output depends on the locale argument. If locale is 'local', then weekday uses local format for its output. If locale is 'en_US', then weekday uses US English.

weekday

[N, S] = weekday(D, form, locale) returns the day of the week using the formats described above for form and locale.

Examples	Either
	[n, s] = weekday(728647)
	or
	[n, s] = weekday('19-Dec-1994')
	returns $n = 2$ and $s = Mon$.
See Also	datenum, datevec, eomday

Purpose	List MATLAB files in folder		
Graphical Interface	As an alternative to the what function, use the Current Folder browser.		
Syntax	what what folderName what className what packageName s = what('folderName')		
Description	what lists the path for the current folder, and lists all files and folders relevant to MATLAB found in the current folder. Files listed are M, MAT, MEX, MDL, and P-files. Folders listed are all class and package folders.		
	what <i>folderName</i> lists path, file, and folder information for <i>folderName</i> . Use an absolute or partial path for <i>folderName</i> .		
	what <i>className</i> lists path, file, and folder information for method folder @ <i>className</i> . For example, what cfit lists the MATLAB files and folders in toolbox/curvefit/curvefit/@cfit.		
	what <i>packageName</i> lists path, file, and folder information for package folder + <i>packageName</i> . For example, what commsrc lists the MATLAB files and folders in toolbox/comm/comm/+commsrc.		
	s = what(' <i>folderName</i> ') returns the results in a structure array with the fields shown in the following table.		
	Field Description		
	path	Path to folder	
	m Cell array of MATLAB program file names		
	mat Cell array of MAT-file names		
	mex Cell array of MEX-file names		

Field	Description
mdl	Cell array of MDL-file names
р	Cell array of P-file names
classes	Cell array of class folders
packages	Cell array of package folders

Examples List Files and Folders Relevant to MATLAB

List the MATLAB files and folders in toolbox/matlab/audiovideo:

what audiovideo

M-files in directory matlabroot\toolbox\matlab\audiovideo

Contents	avifinfo	sound
audiodevinfo	aviinfo	soundsc
audioplayerreg	aviread	wavfinfo
audiorecorderreg	lin2mu	wavplay
audiouniquename	mmcompinfo	wavread
aufinfo	mmfileinfo	wavrecord
auread	movie2avi	wavwrite
auwrite	mu2lin	
avgate	prefspanel	

MAT-files in directory matlabroot\toolbox\matlab\audiovideo

chirp	handel	splat
gong	laughter	train

MEX-files in directory matlabroot\toolbox\matlab\audiovideo

winaudioplayer winaudiorecorder

Classes in directory matlabroot\toolbox\matlab\audiovideo

audioplayer avifile audiorecorder mmreader

Return Names to a Structure

Obtain a structure array containing the file and folder names in toolbox/matlab/general that are relevant to MATLAB:

```
s = what('general')
s =
    path: 'matlabroot:\toolbox\matlab\general'
        m: {89x1 cell}
        mat: {0x1 cell}
        mex: {2x1 cell}
        mdl: {0x1 cell}
        p: {'callgraphviz.p'}
        classes: {'char'}
        packages: {0x1 cell}
```

List Files in a Package

Find the supporting files for one of the packages in the Communications Toolbox product:

```
p1 = what('comm');
p1.packages
ans =
    'commdevice'
    'crc'
    'commsrc'
p2 = what('commsrc');
p2.m
ans =
    'abstractJitter.m'
    'abstractPulse.m'
```

what

```
'combinedjitter.m'
'diracjitter.m'
'periodicjitter.m'
'randomjitter.m'
```

See Also dir, exist, lookfor, ls, mfilename, path, which, who "Managing Files in MATLAB"

Purpose	Release Notes for MathWorks products
Syntax	whatsnew
Description	whatsnew displays the Release Notes in the Help browser, presenting information about new features, problems from previous releases that have been fixed in the current release, and compatibility issues, all organized by product.
See Also	help, version

which

Purpose	Locate functions and files
Graphical Interface	As an alternative to the which function, you can use the "Using the Current Folder Browser" to find files. You can find functions using the Function Browser in the Command Window or Editor.
Syntax	<pre>which fun which classname/fun which private/fun which classname/private/fun which fun1 in fun2 which fun(a,b,c,) which file.ext which fun -all s = which('fun',)</pre>
Description	 which fun displays the full pathname for the argument fun. If fun is a MATLAB function or Simulink model in an M, P, or MDL file on the MATLAB path, then which displays the full pathname for the corresponding file Workspace variable, then which displays a message identifying fun as a variable Method in a loaded Java class, then which displays the package, class, and method name for that method If fun is an overloaded function or method, then which fun returns only the pathname of the first function or method found. which classname/fun displays the full pathname for the file that defines the fun method in MATLAB class, classname. For example, which serial/fopen displays the path for fopen.m in the MATLAB class folder, @serial.

which **private**/fun limits the search to private functions. For example, which private/orthog displays the path for orthog.m in the /private subfolder of toolbox/matlab/elmat.

which classname/private/fun limits the search to private methods defined by the MATLAB class, classname. For example, which dfilt/private/todtf displays the path for todtf.m in the private folder of the dfilt class.

which fun1 in fun2 displays the pathname to function fun1 in the context of file fun2. You can use this form to determine whether a subfunction is being called instead of a function on the path. For example, which get in editpath tells you which get function is called by editpath.m.

During debugging of fun2, using which fun1 gives the same result.

which fun(a,b,c,...) displays the path to the specified function with the given input arguments. For example, which feval(g), when g=inline('sin(x)'), indicates that inline/feval.m would be invoked. which toLowerCase(s), when s=java.lang.String('my Java string'), indicates that the toLowerCase method in class java.lang.String would be invoked.

which file.ext displays the full pathname of the specified file if that file is in the current working folder or on the MATLAB path. To display the path for a file that has no file extension, type "which file." (the period following the filename is required). Use exist to check for the existence of files anywhere else.

which fun **-all** displays the paths to all items on the MATLAB path with the name fun. Such items include methods of instantiated classes. You may use the **-all** qualifier with any of the above formats of the which function.

s = which('fun',...) returns the results of which in the string s. For workspace variables, s is the string 'variable'. You may specify an output variable in any of the above formats of the which function.

If **-all** is used with this form, the output **s** is always a cell array of strings, even if only one string is returned.

which

Examples The statement below indicates that pinv is in the matfun folder of MATLAB.

which pinv
matlabroot\toolbox\matlab\matfun\pinv.m

To find the fopen function used on MATLAB serial class objects

```
which serial/fopen
matlabroot\toolbox\matlab\iofun\@serial\fopen.m % serial method
```

To find the setMonth method used on objects of the Java Date class, the class must first be loaded into MATLAB. The class is loaded when you create an instance of the class:

```
myDate = java.util.Date;
which setMonth
```

MATLAB displays:

setMonth is a Java method % java.util.Date method

When you specify an output variable, which returns a cell array of strings to the variable. You must use the *function* form of which, enclosing all arguments in parentheses and single quotes:

s = which('private/stradd','-all');
whos s
Name Size Bytes Class
s 3x1 562 cell array
Grand total is 146 elements using 562 bytes
See Also dir, doc, exist, lookfor, mfilename, path, type, what, who

Purpose Repeatedly execute statements while condition is true **Syntax** while expression program statements end Description while expression, program statements, end repeatedly executes one or more MATLAB program statements in a loop, continuing until *expression* no longer holds true or until MATLAB encounters a break, or return instruction, thus forcing an immediate exit of the loop code. If MATLAB encounters a continue statement in the loop code, it interrupts execution of the loop code at the location of the continue statement, and begins another iteration of the loop at the while expression statement. *expression* is a MATLAB expression that evaluates to a result of logical 1 (true) or logical 0 (false). expression can be scalar or an array. It must contain all real elements, and the statement all(A(:)) must be equal to logical 1 for the expression to be true. *expression* usually consists of variables or smaller expressions joined by relational operators (e.g., count < limit) or logical functions (e.g., isreal(A)). Simple expressions can be combined by logical operators (&&, ||, -) into compound expressions such as the following. MATLAB evaluates compound expressions from left to right, adhering to "Operator Precedence" rules. (count < limit) && ((height - offset) >= 0) statements is one or more MATLAB statements to be executed only while the *expression* is true or nonzero. The scope of a while statement is always terminated with a matching end. See "Program Control Statements" in the MATLAB Programming Fundamentals documentation for more information on controlling the flow of your program code.

Remarks

Nonscalar Expressions

If the evaluated expression yields a nonscalar value, then every element of this value must be true or nonzero for the entire expression to be considered true. For example, the statement while (A < B) is true only if each element of matrix A is less than its corresponding element in matrix B. See "Example 2 – Nonscalar Expression" on page 2-4457, below.

Partial Evaluation of the Expression Argument

Within the context of an if or while expression, MATLAB does not necessarily evaluate all parts of a logical expression. In some cases it is possible, and often advantageous, to determine whether an expression is true or false through only partial evaluation.

For example, if A equals zero in statement 1 below, then the expression evaluates to false, regardless of the value of B. In this case, there is no need to evaluate B and MATLAB does not do so. In statement 2, if A is nonzero, then the expression is true, regardless of B. Again, MATLAB does not evaluate the latter part of the expression.

1) while (A && B) 2) while (A || B)

You can use this property to your advantage to cause MATLAB to evaluate a part of an expression only if a preceding part evaluates to the desired state. Here are some examples.

```
while (b ~= 0) && (a/b > 18.5)
if exist('myfun.m') && (myfun(x) >= y)
if iscell(A) && all(cellfun('isreal', A))
```

Empty Arrays

In most cases, using while on an empty array returns false. There are some conditions however under which while evaluates as true on an empty array. Two examples of this are

```
A = [];
while all(A), do_something, end
while 1|A, do_something, end
```

Short-Circuiting Behavior

When used in the context of a while or if expression, and only in this context, the element-wise | and & operators use short-circuiting in evaluating their expressions. That is, A|B and A&B ignore the second operand, B, if the first operand, A, is sufficient to determine the result.

See "Short-Circuiting in Elementwise Operators" for more information on this.

Examples Example 1 – Simple while Statement

The variable eps is a tolerance used to determine such things as near singularity and rank. Its initial value is the *machine epsilon*, the distance from 1.0 to the next largest floating-point number on your machine. Its calculation demonstrates while loops.

This example is for the purposes of illustrating while loops only and should not be executed in your MATLAB session. Doing so will disable the eps function from working in that session.

Example 2 – Nonscalar Expression

Given matrices A and B,

 $\begin{array}{ccccccc} A = & & B = & \\ & 1 & 0 & & 1 & 1 \\ & 2 & 3 & & 3 & 4 \end{array}$

Expression	Evaluates As	Because
A < B	false	A(1,1) is not less than $B(1,1)$.
A < (B + 1)	true	Every element of A is less than that same element of B with 1 added.
A & B	false	A(1,2) is false, and B is ignored due to short-circuiting.
B < 5	true	Every element of B is less than 5.

See Also

end, for, break, continue, return, all, any, if, switch

Purpose	Change axes background color
Syntax	<pre>whitebg whitebg(fig) whitebg(ColorSpec) whitebg(fig, ColorSpec) whitebg(fig, ColorSpec) whitebg(fig)</pre>
Description	whitebg complements the colors in the current figure.
	whitebg(fig) complements colors in all figures specified in the vector fig.
	<pre>whitebg(ColorSpec) and whitebg(fig, ColorSpec) change the color of the axes, which are children of the figure, to the color specified by ColorSpec. Without a figure specification, whitebg or whitebg(ColorSpec) affects the current figure and the root's default properties so subsequent plots and new figures use the new colors.</pre>
	whitebg(fig, ColorSpec) sets the default axes background color of the figures in the vector fig to the color specified by ColorSpec. Other axes properties and the figure background color can change as well so that graphs maintain adequate contrast. ColorSpec can be a 1-by-3 RGB color or a color string such as 'white' or 'w'.
	whitebg(fig) complements the colors of the objects in the specified figures. This syntax is typically used to toggle between black and white axes background colors, and is where whitebg gets its name. Include the root window handle (0) in fig to affect the default properties for new windows or for clf reset.
Remarks	whitebg works best in cases where all the axes in the figure have the same background color.
	whitebg changes the colors of the figure's children, with the exception of shaded surfaces. This ensures that all objects are visible against the new background color. whitebg sets the default properties on the root such that all subsequent figures use the new background color.

whitebg

Examples	Set the background color to blue-gray.
	whitebg([0 .5 .6])
	Set the background color to blue.
	whitebg('blue')
See Also	ColorSpec, colordef
	The figure graphics object property InvertHardCopy
	"Color Operations" on page 1-108 for related functions

Purpose	List variables in workspace
Graphical Interface	As an alternative to whos, use the Workspace browser. For information on viewing the contents of MAT-files without loading them, see "Using the Current Folder Browser".
Syntax	<pre>who whos who(variable_list) whos(variable_list) who(variable_list, qualifiers) whos(variable_list, qualifiers) s = who(variable_list, qualifiers) s = whos(variable_list, qualifiers) who variable_list qualifiers whos variable_list qualifiers</pre>
Description	who lists in alphabetical order all variables in the currently active workspace. whos lists in alphabetical order all variables in the currently active workspace along with their sizes and types.
	Note If who or whos is executed within a nested function, the MATLAB software lists the variables in the workspace of that function and in the workspaces of all functions containing that function. See the Remarks section, below. who(variable_list) and whos(variable_list) list only those variables specified in variable_list, where variable_list is a
	comma-delimited list of quoted strings: 'var1', 'var2',, 'varN'. You can use the wildcard character * to display variables that match a pattern. For example, who('A*') finds all variables in the current workspace that start with A.

who(variable_list, qualifiers) and whos(variable_list, qualifiers) list those variables in variable_list that meet all qualifications specified in qualifiers. You can specify any or all of the following qualifiers, and in any order.

Qualifier Syntax	Description	Example
global	List variables in the global workspace.	whos('global')
-file , filename	List variables in the specified MAT-file. Use the full path for filename.	whos('-file', 'mydata')
-regexp , exprlist	List variables that match any of the regular expressions in exprlist.	whos('-regexp', '[AB].', '\w\d')

s = who(variable_list, qualifiers) returns cell array s containing the names of the variables specified in variable_list that meet the conditions specified in qualifiers.

s = whos(variable_list, qualifiers) returns structure s
containing the following fields for the variables specified in
variable_list that meet the conditions specified in qualifiers:

Field Name	Description
name	Name of the variable
size	Dimensions of the variable array
bytes	Number of bytes allocated for the variable array
class	Class of the variable. Set to the string '(unassigned)' if the variable has no value.
global	True if the variable is global; otherwise false

Field Name	Description
sparse	True if the variable is sparse; otherwise false
complex	True if the variable is complex; otherwise false
nesting	 Structure having the following fields: function — Name of the nested or outer function that defines the variable
	 level — Nesting level of that function
persistent	True if the variable is persistent; otherwise false

who variable_list qualifiers and whos variable_list qualifiers are the unquoted forms of the syntax. Both variable_list and qualifiers are space-delimited lists of unquoted strings.

Remarks Nested Functions. When you use who or whos inside of a nested function, MATLAB returns or displays all variables in the workspace of that function, and in the workspaces of all functions in which that function is nested. This applies whether you include calls to who or whos in your function code or if you call who or whos from the MATLAB debugger.

If your code assigns the output of whos to a variable, MATLAB returns the information in a structure array containing the fields described above. If you do not assign the output to a variable, MATLAB displays the information at the Command Window, grouped according to workspace.

If your code assigns the output of who to a variable, MATLAB returns the variable names in a cell array of strings. If you do not assign the output, MATLAB displays the variable names at the Command Window, but not grouped according to workspace. **Compressed Data.** Information returned by the command whos -file is independent of whether the data in that file is compressed or not. The byte counts returned by this command represent the number of bytes data occupies in the MATLAB workspace, and not in the file the data was saved to. See the function reference for save for more information on data compression.

MATLAB Objects. whos -file *filename* does not return the sizes of any MATLAB objects that are stored in file *filename*.

Examples Example 1

Show variable names starting with the letter a:

who a*

Show variables stored in MAT-file mydata.mat:

```
who -file mydata
```

Example 2

Return information on variables stored in file mydata.mat in structure array s:

```
s = whos('-file', 'mydata1')
s =
6x1 struct array with fields:
    name
    size
    bytes
    class
    global
    sparse
    complex
    nesting
    persistent
```

Display the name, size, and class of each of the variables returned by whos:

```
for k=1:length(s)
disp([' 's(k).name ' 'mat2str(s(k).size) ' 's(k).class])
end
        A [1 1] double
      spArray [5 5] double
      strArray [2 5] cell
        x [3 2 2] double
        y [4 5] cell
```

Example 3

Show variables that start with java and end with Array. Also show their dimensions and class name:

whos -file mydata2	-regexp	\ <java.*arra< th=""><th>y \></th></java.*arra<>	y \>
Name	Size	Bytes	Class
javaChrArray	3x1		java.lang.String[][][]
javaDblArray	4x1		java.lang.Double[][]
javaIntArray	14x1		java.lang.Integer[][]

Example 4

The function shown here uses variables with persistent, global, sparse, and complex attributes:

```
function show_attributes
persistent p;
global g;
o = 1; g = 2;
s = sparse(eye(5));
c = [4+5i 9-3i 7+6i];
whos
```

When the function is run, whos displays these attributes:

show_attributes

· · · · · · · · · · · ·	Na	ame Size	e Bytes	Class	Attributes
s 5x5 84 double sparse	g	1x1	8	double	•

Example 5

Function whos_demo contains two nested functions. One of these functions calls whos; the other calls who:

```
function whos demo
date time = datestr(now);
[str pos] = textscan(date time, '%s%s%s', ...
                     1, 'delimiter', '- :');
get date(str);
str = textscan(date time(pos+1:end), '%s%s%s', ...
               1, 'delimiter', '- :');
get time(str);
   function get date(d)
      day = d\{1\}; mon = d\{2\}; year = d\{3\};
      whos
   end
   function get time(t)
      hour = t{1}; min = t{2}; sec = t{3};
      who
   end
end
```

When nested function get_date calls whos, MATLAB displays information on the variables in all workspaces that are in scope at the time. This includes nested function get_date and also the function in which it is nested, whos_demo. The information is grouped by workspace:

whos_demo Name	Size	Bytes	Class
get_dat	te		
d	1x3	378	cell
day	1x1	64	cell
mon	1x1	66	cell
year	1x1	68	cell
whos_de	emo		
ans	0x0	0	(unassigned)
date_time	1x20	40	char
pos	1x1	8	double
str	1x3	378	cell

When nested function get_time calls who, MATLAB displays names of the variables in the workspaces that are in scope at the time. This includes nested function get_time and also the function in which it is nested, whos_demo. The information is not grouped by workspace in this case:

Your variables are:

hour	min	sec	t	ans	date_time
pos	str				

See Also assignin, clear, computer, dir, evalin, exist, inmem, load, save, what, workspace

"MATLAB Workspace" in the Desktop Tools and Development Environment documentation

wilkinson

Purpose	Wilkinson's eigenvalue test matrix									
Syntax	W = wilkinson(n)									
Description	W = wilkinson(n) returns one of J. H. Wilkinson's eigenvalue test matrices. It is a symmetric, tridiagonal matrix with pairs of nearly, but not exactly, equal eigenvalues.									
Examples	wilkinson(7)									
	ans =									
	3		1	0	0	0	0	0		
	1		2	1	0	0	0	0		
	0		1	1	1	0	0	0		
	0		0	1	0	1	0	0		
	0		0	0	1	1	1	0		
	0		0	0	0	1	2	1		
	0		0	0	0	0	1	3		
	The most frequently used case is wilkinson(21). Its two largest eigenvalues are both about 10.746; they agree to 14, but not to 15, decimal places.									

See Also eig, gallery, pascal

winopen

Purpose	Open file in appropriate application (Windows)
Syntax	winopen(fileName)
Description	winopen(fileName) opens fileName in the associated Microsoft Windows application. The application is associated with the extension in fileName in the Windows operating system. filename is a string enclosed in single quotes. winopen uses a Windows shell command, and performs the same action as double-clicking the file in the Windows Explorer program. That is, winopen calls the application associated the file extension to open the file. Use an absolute or relative path for fileName.
Examples	Open the file thesis.doc, located in the current folder, in the Microsoft Word program: winopen('thesis.doc')
	Open myresults.html in the system Web browser: winopen('D:/myfiles/myresults.html')
	On Microsoft Windows platforms, open the current folder in the Windows Explorer tool: winopen(cd)
	To open a file on the MATLAB path, use winopen with which. For example, to open the meshgrid function in the Editor, use: winopen(which(meshgrid))
See Also	dos, open, web

"Managing Files in MATLAB"

Purpose	Item from Windows registry									
Syntax	valnames = winqueryreg(' name ', 'rootkey', 'subkey') value = winqueryreg('rootkey', 'subkey', 'valname') value = winqueryreg('rootkey', 'subkey')									
Description	<pre>valnames = winqueryreg('name', 'rootkey', 'subkey') returns all value names in rootkey\subkey of Microsoft Windows operating system registry to a cell array of strings. The first argument is the literal quoted string, 'name'.</pre>									
	<pre>value = winqueryreg('rootkey', 'subkey', 'valname') returns the value for value name valname in rootkey\subkey.</pre>									
	If the value retrieved from the registry is a string, winqueryreg returns a string. If the value is a 32-bit integer, winqueryreg returns the value as an integer of the MATLAB software type int32.									
	<pre>value = winqueryreg('rootkey', 'subkey') returns a value in rootkey\subkey that has no value name property.</pre>									
	Note The literal name argument and the rootkey argument are case-sensitive. The subkey and valname arguments are not.									
Remarks	This function works only for the following registry value types:									
	• strings (REG_SZ)									
	• expanded strings (REG_EXPAND_SZ)									
	• 32-bit integer (REG_DWORD)									
Examples	Example 1									
	Get the value of CLSID for the MATLAB sample Microsoft COM control mwsampctrl.2:									
	winqueryreg 'HKEY_CLASSES_ROOT' 'mwsamp.mwsampctrl.2\clsid'									

```
ans = {5771A80A-2294-4CAC-A75B-157DCDDD3653}
```

Example 2

Get a list in variable mousechar for registry subkey Mouse, which is under subkey Control Panel, which is under root key HKEY_CURRENT_USER.

```
mousechar = winqueryreg('name', 'HKEY_CURRENT_USER', ...
'control panel\mouse');
```

For each name in the mousechar list, get its value from the registry and then display the name and its value:

```
for k=1:length(mousechar)
   setting = winqueryreg('HKEY_CURRENT_USER', ...
        'control panel\mouse', mousechar{k});
   str = sprintf('%s = %s', mousechar{k}, num2str(setting));
   disp(str)
   end
ActiveWindowTracking = 0
DoubleClickHeight = 4
DoubleClickSpeed = 830
DoubleClickWidth = 4
MouseSpeed = 1
MouseThreshold1 = 6
MouseThreshold2 = 10
SnapToDefaultButton = 0
SwapMouseButtons = 0
```

Purpose	Determine whether file contains 1-2-3 WK1 worksheet					
	Note wk1finfo will be removed in a future version.					
Syntax	[extens, typ] = wk1finfo(filename)					
Description	<pre>[extens, typ] = wk1finfo(filename) returns the string WK1' in extens, and ' 1-2-3 Spreadsheet' in typ if the file filename contains a readable worksheet. The filename input is a string enclosed in single quotes.</pre>					
Examples	<pre>This example returns information on spreadsheet file matA.wk1: [extens, typ] = wk1finfo('matA.wk1') extens = WK1 typ = 123 Spreadsheet</pre>					
See Also	xlsread, xlswrite, dlmread, dlmwrite					

wk1read

Purpose	Read Lotus 1-2-3 WK1 spreadsheet file into matrix									
	Note wk1read will be removed in a future version.									
Syntax	<pre>M = wk1read(filename) M = wk1read(filename,r,c) M = wk1read(filename,r,c,range)</pre>									
Description	<pre>M = wk1read(filename) reads a Lotus1-2-3 WK1 spreadsheet file into the matrix M. The filename input is a string enclosed in single quotes.</pre>									
	M = wklread(filename,r,c) starts reading at the row-column cell offset specified by (r,c). r and c are zero based so that r=0, c=0 specifies the first value in the file.									
	M = wk1read(filename,r,c,range) reads the range of values specified by the parameter range, where range can be									
	• A four-element vector specifying the cell range in the format									
	[upper_left_row upper_left_col lower_right_row lower_right_col]									
	column									
	row MATLAB Matrix									

~

• A cell range specified as a string, for example, 'A1...C5'

• A named range specified as a string, for example, 'Sales'

Examples Create a 8-by-8 matrix A and export it to Lotus spreadsheet matA.wk1:

A = [1:8; A =	11:18;	21:28	3; 31:3	38; 41	:48; 5	1:58; (61:68;	71:78]
1	2	3	4	5	6	7	8	
11	12	13	14	15	16	17	18	
21	22	23	24	25	26	27	28	
31	32	33	34	35	36	37	38	
41	42	43	44	45	46	47	48	
51	52	53	54	55	56	57	58	
61	62	63	64	65	66	67	68	
71	72	73	74	75	76	77	78	

wk1write('matA.wk1', A);

To read in a limited block of the spreadsheet data, specify the upper left row and column of the block using zero-based indexing:

М	=	wk1	read('ma	atA.wk	(1', 3,	2)	
М	=						
		33	34	35	36	37	38
		43	44	45	46	47	48
		53	54	55	56	57	58
		63	64	65	66	67	68
		73	74	75	76	77	78

To select a more restricted block of data, you can specify both the upper left and lower right corners of the block you want imported. Read in a range of values from row 4, column 3 (defining the upper left corner) to row 6, column 6 (defining the lower right corner). Note that, unlike the second and third arguments, the range argument [4 3 6 6] is one-based:

wk1read

See Also xlsread


Purpose Write matrix to Lotus 1-2-3 WK1 spreadsheet file

Note wk1write will be removed in a future version.

Syntax wk1write(filename,M)
 wk1write(filename,M,r,c)

Description wk1write(filename,M) writes the matrix M into a Lotus1-2-3 WK1 spreadsheet file named filename. The filename input is a string enclosed in single quotes.

wk1write(filename,M,r,c) writes the matrix starting at the spreadsheet location (r,c). r and c are zero based so that r=0, c=0 specifies the first cell in the spreadsheet.



Examples

Write a 4-by-5 matrix A to spreadsheet file matA.wk1. Place the matrix with its upper left corner at row 2, column 3 using zero-based indexing:

A = [1:5; 11:15; 21:25; 31:35]A = wk1write('matA.wk1', A, 2, 3) M = wk1read('matA.wk1') М =

dlmwrite, dlmread, xlswrite, xlsread

Open Workspace browser to manage workspace
As an alternative to the workspace function, select Desktop > Workspace in the MATLAB desktop.
workspace
workspace displays the Workspace browser, a graphical user interface that allows you to view and manage the contents of the workspace in MATLAB. It provides a graphical representation of the whos display, and allows you to perform the equivalent of the clear, load, open, and save functions.
The Workspace browser also displays and automatically updates statistical calculations for each variable, which you can choose to show or hide.

🗎 🖬 🖥 覧	i 🌢 🖪 🕅 ·	- Stack: Base 💌			
Name 🛆	Class	Value	Min	Max	Mean
A	double	<4x4 double>	1	16	8.5000
C C	cell	<1x3 cell>			
🗄 R	double	<3x4x5 double>	-2.05	1.5929	-0.1533
E S	struct	<1x3 struct>			
🕂 a	double	<4x4 double>	1	16	8.5000
🕂 ans	double	<3x4x5 double>	-2.05	1.5929	-0.1533
🕂 avg_score	double	81.3333	81.3	81.3	81.3333
🕂 b	double	<4x4 double>	1	16	8.5000
✓	logical	<4x4 logical>			
ab names	char	<3x12 char>			
🕂 nn	double	[-6.3377 ,-0.2857 ,	-7.67	-0.28	-5.6941
🕂 s1	single	25.7830	25.7	25.7	25.7830
e scores	double	[83,91,70]	70	91	81.3333
ab t	char	'Hello'			
🏹 td	TensileData	<1x1 TensileData>			
ab V	char	<2x5 char>			
🕂 w1	double (complex)	2.0000 + 3.0000i	2.00	2.00	2.0000 + .
🕂 x	int16	325	325	325	
🛨 y	uint32	[9900,26025,39600]	9900	39600	
🕂 z	double	-Inf	-Inf	-Inf	-Inf

You can edit a value directly in the Workspace browser for small numeric and character arrays. To see and edit a graphical representation of larger variables and for other classes, double-click the variable in the Workspace browser. The variable displays in the Variable Editor, where you can view the full contents and make changes. See Also openvar, who "MATLAB Workspace"

Tiff.write

Purpose	Write entire image
Syntax	tiffobj.write(imageData) tiffobj.write(Y,Cb,Cr)
Description	tiffobj.write(imageData) writes imageData to TIFF file associated with the Tiff object, tiffobj. The write method breaks the data into strips or tiles, depending on the value of the RowsPerStrip tag, or the TileLength and TileWidth tags.
	tiffobj.write(Y,Cb,Cr) writes the YCbCr component data to the TIFF file.
See Also	Tiff.writeDirectory
Tutorials	• "Exporting Image Data and Metadata to TIFF Files"

Purpose	Create new IFD and make it current IFD
Syntax	<pre>tiffobj.writeDirectory()</pre>
Description	tiffobj.writeDirectory() create a new image file directory (IFD) and makes it the current IFD. Tiff object methods operate on the current IFD. If you are creating a TIFF file that only contains one image, you do not need to use this method. With single-image TIFF files, just close the Tiff object to write data to the file.
Examples	<pre>Open a TIFF file for modification and create a new IFD in the file. writeDirectory makes the newly created IFD the current IFD. Replace the name myfile.tif with the name of a TIFF file on your MATLAB path. t = Tiff('myfile.tif', 'r+'); dnum = t.currentDirectory(); t.writeDirectory(); dnum = t.currentDirectory();</pre>
References	This method corresponds to the TIFFWriteDirectory function in the LibTIFF C API. To use this method, you must be familiar with LibTIFF version 3.7.1, as well as the TIFF specification and technical notes. View this documentation at LibTIFF - TIFF Library and Utilities.
See Also	Tiff.write Tiff.close
Tutorials	"Exporting Image Data and Metadata to TIFF Files""Reading Image Data and Metadata from TIFF Files"

Tiff.writeEncodedStrip

Purpose	Write data to specified strip
Syntax	tiffobj.writeEncodedStrip(stripNumber,imageData) tiffobj.writeEncodedStrip(stripNumber,Y,Cb,Cr)
Description	tiffobj.writeEncodedStrip(stripNumber,imageData) writes the data in imageData to the strip specified by stripNumber. Strip identification numbers are one-based. If imageData has fewer bytes than fit into a strip, writeEncodedStrip silently pads the strip. If imageData has more bytes than fit into a strip, writeEncodedStrip issues a warning and truncates the data. To determine the size of a strip, view the value of the RowsPerStrip tag.
	tiffobj.writeEncodedStrip(stripNumber,Y,Cb,Cr) writes the YCbCr component data to the specified tile. You must set the YCbCrSubSampling tag.
Examples	Open a Tiff object for modification. Replace myfile.tif with the name of a TIFF file on your MATLAB path. The folder in which you run the example must be writable.
	<pre>t = Tiff('myfile.tif', 'r+');</pre>
	<pre>if ~t.isTiled() width = t.getTag('ImageWidth'); height = t.getTag('RowsPerStrip'); numSamples = t.getTag('SamplesPerPixel'); imageData = zeros(height,width,numSamples,'uint8'); t.writeEncodedStrip(1,imageData); end</pre>
References	This method corresponds to the TIFFWriteEncodedStrip function in the LibTIFF C API. To use this method, you must be familiar with LibTIFF version 3.7.1, as well as the TIFF specification and technical notes. View this documentation at LibTIFF - TIFF Library and Utilities.
See Also	Tiff.writeEncodedTile

Tutorials • "Exporting Image Data and Metadata to TIFF Files"

• "Reading Image Data and Metadata from TIFF Files"

Tiff.writeEncodedTile

Purpose	Write data to specified tile
Syntax	<pre>tiffobj.writeEncodedTile(tileNumber,imageData) tiffobj.writeEncodedTile(tileNumber,Y,Cb,Cr)</pre>
Description	tiffobj.writeEncodedTile(tileNumber,imageData) writes the data in imageData to the tile specified by tileNumber. Tile identification numbers are one-based. If imageData has fewer bytes than fit into a tile, writeEncodedTile silently pads the tile. If imageData has more bytes than fit into a tile, writeEncodedTile issues a warning and truncates the data. To determine the size of a tile, view the value of the tileLength and tileWidth tags.
	tiffobj.writeEncodedTile(tileNumber,Y,Cb,Cr) writes the YCbCr component data to the specified tile. You must set the YCbCrSubSampling tags.
Examples	Open a TIFF file for modification. Replace myfile.tif with the name of a TIFF file on your MATLAB path.
	<pre>t = Tiff('myfile.tif', 'r+');</pre>
	<pre>if t.isTiled() width = t.getTag('tileWidth'); height = t.getTag('tileLength'); numSamples = t.getTag('SamplesPerPixel'); imageData = zeros(height,width,numSamples,'uint8'); t.writeEncodedTile(1,imageData); end</pre>
References	This method corresponds to the TIFFWriteEncodedTile function in the LibTIFF C API. To use this method, you must be familiar with LibTIFF version 3.7.1, as well as the TIFF specification and technical notes. View this documentation at LibTIFF - TIFF Library and Utilities.
See Also	Tiff.writeEncodedStrip

Tutorials • "Exporting Image Data and Metadata to TIFF Files"

• "Reading Image Data and Metadata from TIFF Files"

xlabel, ylabel, zlabel

Purpose	Label <i>x</i> -, <i>y</i> -, and <i>z</i> -axis
GUI Alternative	To control the presence and appearance of axis labels on a graph, use the Property Editor, one of the plotting tools . For details, see The Property Editor in the MATLAB Graphics documentation.
Syntax	<pre>xlabel('string') xlabel(fname) xlabel(,'PropertyName',PropertyValue,) xlabel(axes_handle,) h = xlabel()</pre>
	<pre>ylabel() ylabel(axes_handle,) h = ylabel()</pre>
	<pre>zlabel() zlabel(axes_handle,) h = zlabel()</pre>
Description	Each axes graphics object can have one label for the x -, y -, and z -axis. The label appears beneath its respective axis in a two-dimensional plot and to the side or beneath the axis in a three-dimensional plot.
	xlabel('string') labels the x-axis of the current axes.
	xlabel(fname) evaluates the function fname, which must return a string, then displays the string beside the <i>x</i> -axis.
	xlabel(, ' <i>PropertyName</i> ', PropertyValue,) specifies property name and property value pairs for the text graphics object created by xlabel.

	xlabel(axes_handle,), ylabel(axes_handle,), and zlabel(axes_handle,) plot into the axes with handle axes_handle instead of the current axes (gca).
	h = xlabel(), $h = ylabel()$, and $h = zlabel()$ return the handle to the text object used as the label.
	ylabel() and zlabel() label the y-axis and z-axis, respectively, of the current axes.
Remarks	Reissuing an xlabel, ylabel, or zlabel command causes the new label to replace the old label.
	For three-dimensional graphics, MATLAB puts the label in the front or side, so that it is never hidden by the plot.
Examples	Create a multiline label for the <i>x</i> -axis using a multiline cell array:
	<pre>xlabel({'first line';'second line'})</pre>
	Create a bold label for the <i>y</i> -axis that contains a single quote:
	ylabel('George''s Popularity','fontsize',12,'fontweight','b')
See Also	strings, text, title
	"Annotating Plots" on page 1-97 for related functions
	"Adding Axis Labels to Graphs" for more information about labeling axes


xlim, ylim, zlim

Purpose	Set or query axis limits
GUI Alternative	To control the upper and lower axis limits on a graph, use the Property Editor, one of the plotting tools . For details, see The Property Editor in the MATLAB Graphics documentation.
Syntax	<pre>xlim xlim([xmin xmax]) xlim('mode') xlim('auto') xlim('manual') xlim(axes_handle,)</pre>
	Note that the syntax for each of these three functions is the same; only the xlim function is used for simplicity. Each operates on the respective x -, y -, or z -axis.
Description	xlim with no arguments returns the respective limits of the current axes.
	<pre>xlim([xmin xmax]) sets the axis limits in the current axes to the specified values.</pre>
	<pre>xlim('mode') returns the current value of the axis limits mode, which can be either auto (the default) or manual.</pre>
	xlim('auto') sets the axis limit mode to auto.
	xlim('manual') sets the respective axis limit mode to manual.
	<pre>xlim(axes_handle,) performs the set or query on the axes identified by the first argument, axes_handle. When you do not specify an axes handle, these functions operate on the current axes.</pre>
Remarks	xlim, ylim, and zlim set or query values of the axes object XLim, YLim, ZLim, and XLimMode, YLimMode, ZLimMode properties.
	When the axis limit modes are auto (the default), MATLAB uses limits that span the range of the data being displayed and are round numbers.

Setting a value for any of the limits also sets the corresponding mode to manual. Note that high-level plotting functions like plot and surf reset both the modes and the limits. If you set the limits on an existing graph and want to maintain these limits while adding more graphs, use the hold command.

Examples This example illustrates how to set the *x*- and *y*-axis limits to match the actual range of the data, rather than the rounded values of [-2 3] for the *x*-axis and [-2 4] for the *y*-axis originally selected by MATLAB.

```
[x,y] = meshgrid([-1.75:.2:3.25]);
z = x.*exp(-x.^2-y.^2);
surf(x,y,z)
xlim([-1.75 3.25])
ylim([-1.75 3.25])
```



xlim, ylim, zlim

See Also

axis

The axes properties XLim, YLim, ZLim

"Aspect Ratio and Axis Limits" on page 1-110 for related functions

Understanding Axes Aspect Ratio for more information on how axis limits affect the axes

Purpose	Determine whether file contains a Microsoft Excel spreadsheet
Syntax	typ = xlsfinfo(filename) [typ, desc] = xlsfinfo(filename) [typ, desc, fmt] = xlsfinfo(filename) xlsfinfo filename
Description	typ = xlsfinfo(filename) returns the string 'Microsoft Excel Spreadsheet' if the file specified by filename is an Excel file that can be read by the MATLAB xlsread function. Otherwise, typ is the empty string, (''). The filename input is a string enclosed in single quotation marks.
	[typ, desc] = xlsfinfo(filename) returns in desc a cell array of strings containing the names of each spreadsheet in the file. If a spreadsheet is unreadable, the cell in desc that represents that spreadsheet contains an error message.
	<pre>[typ, desc, fmt] = xlsfinfo(filename) returns in the fmt output a string containing the Excel-reported file format. On UNIX systems, or on Windows systems without Excel software installed, xlsfinfo returns fmt as an empty string, ('').</pre>
	xlsfinfo filename is the command format for xlsfinfo. It returns only the first output, typ, assigning it to the MATLAB default variable ans.
Remarks	If your system has Excel for Windows installed, xlsfinfo uses the COM server to obtain information. This server is part of the typical installation of Excel for Windows. If the COM server is unavailable, xlsfinfo returns a warning indicating that it cannot start an ActiveX server. To establish connectivity with the COM server, you might need to reinstall your Excel software.
Examples	<pre>Get information about an .xls file: [typ, desc, fmt] = xlsfinfo('myaccount.xls')</pre>

```
typ =
   Microsoft Excel Spreadsheet

desc =
   'Sheet1' 'Income' 'Expenses'
fmt =
   xlWorkbookNormal
```

Export the .xls file to comma-separated value (CSV) format. Use xlsfinfo to see the format of the exported file:

```
[typ, desc, fmt] = xlsfinfo('myaccount.csv');
fmt
fmt =
     xlCSV
```

Export the .xls file to HTML format. xlsfinfo returns the following format string:

```
[typ, desc, fmt] = xlsfinfo('myaccount.html');
fmt
fmt =
```

```
xlHtml
```

Export the .xls file to XML format. xlsfinfo returns the following format string:

```
[typ, desc, fmt] = xlsfinfo('myaccount.xml');
fmt
fmt =
    xlXMLSpreadsheet
```

See Also xlsread, xlswrite

Purpose	Read Microsoft Excel spreadsheet file
Syntax (1997)	<pre>num = xlsread(filename) num = xlsread(filename, -1) num = xlsread(filename, sheet) num = xlsread(filename, range) num = xlsread(filename, sheet, range) num = xlsread(filename, sheet, range, 'basic') num = xlsread(filename,, functionhandle) [num, txt] = xlsread(filename,) [num, txt, raw] = xlsread(filename,) [num, txt, raw, X] = xlsread(filename,, functionhandle) xlsread filename sheet range basic</pre>
Description	<pre>num = xlsread(filename) returns numeric data in double array num from the first sheet in the Microsoft Excel spreadsheet file named filename. The filename argument is a string enclosed in single quotation marks. xlsread ignores any <i>outer</i> rows or columns of the spreadsheet that contain no numeric data. If there are single or multiple nonnumeric</pre>
	rows at the top or bottom, or single or multiple nonnumeric columns to the left or right, xlsread does not include these rows or columns in the output. For example, xlsread ignores one or more header lines appearing at the top of a spreadsheet.
	Any <i>inner</i> rows or columns in which some or all cells contain nonnumeric data are <i>not</i> ignored. Instead, xlsread assigns a value of NaN to the nonnumeric cells.
	<pre>num = xlsread(filename, -1) opens the file filename in an Excel window, enabling you to interactively select the worksheet to read and the range of data on that worksheet to import.</pre>
	To import an entire worksheet, first select the sheet in the Excel window, and then click the OK button in the Data Selection Dialog box. To import a certain range of data from the sheet, select the worksheet in the Excel window, drag and drop the mouse over the desired range, and then click OK . (See "COM Server Requirements" on page 2-4498 below.)

xlsread

num = xlsread(filename, sheet) reads the specified worksheet, where sheet is either a positive, double scalar value or a quoted string containing the sheet name. To determine the names of the sheets in a spreadsheet file, use xlsfinfo.

num = xlsread(filename, range) reads data from a specific rectangular region of the default worksheet (Sheet1). (See "COM Server Requirements" on page 2-4498 below.)

Specify range using the syntax 'C1:C2', where C1 and C2 are two opposing corners that define the region to be read. For example, 'D2:H4' represents the 3-by-5 rectangular region between the two corners D2 and H4 on the worksheet. The range input is not case sensitive and uses Excel A1 reference style. For more information on this reference style, see Excel help.

Note If you specify only two inputs, xlsread must decide whether the second input refers to a sheet or a range. To specify a range (even a range of a single cell), include a colon character in the input string (e.g., 'D2:H4'). If you do not include a colon character (e.g., 'sales' or 'D2'), xlsread interprets the second input as the name or index of a worksheet.

num = xlsread(filename, sheet, range) reads data from a specific rectangular region (range) of the worksheet specified by sheet. If you specify both sheet and range, range can refer to a named range that you defined in the Excel file. (For more information on named ranges, see the Excel help.) See the previous two syntax formats for further explanation of the sheet and range inputs. (Also, see "COM Server Requirements" on page 2-4498 below.)

num = xlsread(filename, sheet, range, 'basic') imports data
from the spreadsheet in basic import mode. xlsread uses this mode on
systems where Excel software is not installed. Import ability is limited.
xlsread ignores the value for range and, consequently, imports the
whole active range of a sheet. (You can set range to the empty string

('').) Also, in basic mode, sheet is case sensitive and must be a quoted string.

num = xlsread(filename, ..., functionhandle) calls the function associated with functionhandle just prior to obtaining spreadsheet values. This enables you to operate on the spreadsheet data (for example, convert it to a numeric type) before reading it in. (See "COM Server Requirements" on page 2-4498 below.)

You can write your own custom function and pass a handle to this function to xlsread. When xlsread executes, it reads from the spreadsheet, executes your function on the data read from the spreadsheet, and returns the final results to you. When xlsread calls your function, it passes a range interface from the Excel application to provide access to the data read from the spreadsheet. Your function must include this interface both as an input and output argument. Example 5 below shows how you might use this syntax.

For more information, see "Function Handles" in the MATLAB Programming Fundamentals documentation.

[num, txt]= xlsread(filename, ...) returns numeric data in array num and text data in cell array txt. All cells in txt that correspond to numeric data contain the empty string.

[num, txt, raw] = xlsread(filename, ...) returns numeric and text data in num and txt, and unprocessed cell content in cell array raw, which contains both numeric and text data. (See "COM Server Requirements" on page 2-4498 below.)

If the Excel file includes cells with undefined values (such as '#N/A'), xlsread returns these values as '#N/A' in the txt output, and as 'ActiveX VT_ERROR:' in the raw output.

[num, txt, raw, X] = xlsread(filename, ..., functionhandle) calls the function associated with functionhandle just prior to reading from the spreadsheet file. This syntax returns one additional output X from the function mapped to by functionhandle. Example 6 below shows how you might use this syntax. (See "COM Server Requirements" on page 2-4498 below.) xlsread filename sheet range **basic** is an example of the command format for xlsread, showing its usage with all input arguments specified. When using this format, you must specify sheet as a string, (for example, Income or Sheet4) and not a numeric index. If the sheet name contains space characters, then quotation marks are required around the string, (for example, 'Income 2002').

Remarks COM Server Requirements

The typical installation of Excel for Windows includes the ability to start a COM server. With Excel for Windows installed, you can use xlsread to read any file format recognized by your version of Excel, including XLS, XLSX, XLSB, XLSM, and HTML-based formats. xlsread can read data saved in files that are currently open in Excel for Windows.

If your system does not have Excel for Windows installed, or MATLAB cannot access the COM server, xlsread operates in basic mode. In this mode, xlsread only reads XLS files.

The following five syntax formats are supported only on computer systems able to start a COM server from a MATLAB session. They are not supported in basic mode.

```
num = xlsread(filename, -1)
num = xlsread(filename, 'range')
num = xlsread(filename, sheet, 'range')
num = xlsread(filename, ..., functionhandle)
[num, txt, raw, opt] = xlsread(filename, ..., functionhandle)
```

Handling Excel Date Values

MATLAB functions import all formatted dates as strings. To import a numeric date, the date field in Excel must have a numeric format.

Both Excel and MATLAB applications represent numeric dates as a number of serial days elapsed from a specific reference date. However, Excel and MATLAB use different reference dates:

Application	Reference Date
MATLAB	January 0, 0000
Excel for Windows	January 1, 1900
Excel for the Macintosh	January 2, 1904

Therefore, you must convert any numeric date that you import before you process it in MATLAB. For more information, see "Converting Dates" in the MATLAB Data Import and Export documentation.

Consider using the functionhandle parameter for this conversion, discussed in the Syntax Description and in Example 5 and Example 6.

Examples Example 1 – Reading Numeric Data

The Microsoft Excel spreadsheet file testdata1.xls contains this data:

To read this data into MATLAB, use this command:

```
A = xlsread('testdata1.xls')
A =
1 6
2 7
3 8
4 9
5 10
```

Example 2 – Handling Text Data

The Microsoft Excel spreadsheet file testdata2.xls contains a mix of numeric and text data:

1 6

xlsread

2 7 3 8 4 9 5 text

xlsread puts a NaN in place of the text data in the result:

```
A = xlsread('testdata2.xls')
A =
1 6
2 7
3 8
4 9
5 NaN
```

Example 3 – Selecting a Range of Data

To import only rows 4 and 5 from worksheet 1, specify the range as 'A4:B5':

Example 4 – Handling Files with Row or Column Headers

A Microsoft Excel worksheet labeled Temperatures in the file tempdata.xls contains two columns of numeric data with text headers for each column:

Time	Temp
12	98
13	99
14	97

If you want to import only the numeric data, use xlsread with a single return argument. Specify the filename and sheet name as inputs.

xlsread ignores any leading row or column of text in the numeric result.

```
ndata = xlsread('tempdata.xls', 'Temperatures')
ndata =
12 98
13 99
14 97
```

To import both the numeric data and the text data, specify two return values for xlsread:

```
[ndata, headertext] = xlsread('tempdata.xls', 'Temperatures')
ndata =
    12    98
    13    99
    14    97
headertext =
    'Time' 'Temp'
```

Example 5 - Passing a Function Handle

This example calls xlsread twice, the first time as a simple read from a file, and the second time requesting that xlsread execute some user-defined modifications on the data prior to returning the results of the read. A user-written function, setMinMax, that you pass as a function handle in the call to xlsread, performs these modifications. When xlsread executes, it reads from the spreadsheet, executes the function on the data read from the spreadsheet, and returns the final results to you.

Note The function passed to xlsread operates on the copy of the data read from the spreadsheet. It does not modify data in the spreadsheet itself.

Read a 10-by-3 numeric array from Excel spreadsheet testsheet.xls with a simple xlsread statement that does not pass a function handle. The returned values range from -587 to +4,149:

```
arr = xlsread('testsheet.xls')
arr =
  1.0e+003 *
    1.0020
              4.1490
                         0.2300
    1.0750
              0.1220
                        -0.4550
   -0.0301
              3.0560
                         0.2471
    0.4070
              0.1420
                        -0.2472
    2.1160
                        -0.5870
             -0.0557
    0.4040
              2,9280
                         0.0265
    0.1723
              3.4440
                         0.1112
    4.1180
              0.1820
                         2.8630
    0.9000
              0.0573
                         1.9750
    0.0163
              0.2000
                        -0.0223
```

In preparation for the second part of this example, write a function setMinMax that restricts the values returned from the read to be in the range of 0 to 2000. You need to pass this function in the call to xlsread, which then executes the function on the data it has read before returning it to you.

When xlsread calls your function, it passes an Excel range interface to provide access to the data read from the spreadsheet. This is shown as DataRange in this example. Your function must include this interface both as an input and output argument. The output argument allows your function to pass modified data back to xlsread:

```
function [DataRange] = setMinMax(DataRange)
maxval = 2000; minval = 0;
for k = 1:DataRange.Count
   v = DataRange.Value{k};
   if v > maxval || v < minval
        if v > maxval
        DataRange.Value{k} = maxval;
   }
}
```

```
else
DataRange.Value{k} = minval;
end
end
end
```

Now call xlsread, passing a function handle for the setMinMax function as the final argument, using '' as placeholders for sheet, range, and import mode. After this call, all values are between 0 and 2000:

```
arr = xlsread('testsheet.xls', '', '', @setMinMax)
arr =
  1.0e+003 *
    1.0020
              2.0000
                         0.2300
    1.0750
              0.1220
                              0
              2.0000
                         0.2471
         0
    0.4070
              0.1420
                              0
                              0
    2.0000
                    0
    0.4040
              2.0000
                         0.0265
    0.1723
              2.0000
                         0.1112
    2.0000
              0.1820
                         2.0000
    0.9000
                         1.9750
              0.0573
    0.0163
              0.2000
                              0
```

Example 6 – Passing a Function Handle with Additional Output

This example adds onto the previous one by returning an additional output from the call to setMinMax. Modify the function so that it not only limits the range of values returned, but also returns the indices of the altered elements. Return this information in a new output argument, indices:

```
function [DataRange, indices] = setMinMax(DataRange)
maxval = 2000; minval = 0;
indices = [];
for k = 1:DataRange.Count
    v = DataRange.Value{k};
```

```
if v > maxval || v < minval
    if v > maxval
        DataRange.Value{k} = maxval;
        else
        DataRange.Value{k} = minval;
        end
        indices = [indices k];
        end
end
```

When you call xlsread this time, account for the three initial outputs, and add a fourth called idx to accept the indices returned from setMinMax:

[arr txt raw idx] = xlsread('testsheet.xls', ... '', '', '', @setMinMax); idx idx = 3 5 8 11 13 15 16 17 22 24 25 28 30 arr arr = 1.0e+003 * 0.2300 1.0020 2.0000 1.0750 0.1220 0 0 2.0000 0.2471 0.4070 0.1420 0 2.0000 0 0 0.4040 2.0000 0.0265 0.1723 2.0000 0.1112 2.0000 0.1820 2.0000 1.9750 0.9000 0.0573 0.0163 0.2000 0 xlswrite, xlsfinfo, importdata, uiimport, textscan,

function_handle

See Also

Purpose	Write Microsoft Excel spreadsheet file
Syntax	<pre>xlswrite(filename, M) xlswrite(filename, M, sheet) xlswrite(filename, M, range) xlswrite(filename, M, sheet, range) status = xlswrite(filename,) [status, message] = xlswrite(filename,) xlswrite filename M sheet range</pre>
Description	xlswrite(filename, M) writes matrix M to the Excel file filename. The filename input is a string enclosed in single quotation marks, and should include the file extension. The matrix M is an m-by-n numeric or character array or, if each cell contains a single element, a cell array (see Example 2). xlswrite writes the matrix data to the first worksheet in the file, starting at cell A1.
	If filename does not exist, xlswrite creates a new file. The file extension you provide as part of filename determines the Excel format that xlswrite uses for the new file. An extension of .xls creates a worksheet compatible with Excel 97-2003 software. Use extensions .xlsx, .xlsb, or .xlsm to create worksheets in Excel 2007 file formats. The maximum size of the matrix M depends on the associated Excel version. (For more information on Excel specifications and limits, see Excel help.)
	xlswrite(filename, M, sheet) writes matrix M to the specified worksheet sheet in the file filename. The sheet argument can be either a positive, double scalar value representing the worksheet index, or a quoted string containing the sheet name. The sheet argument cannot contain a colon.
	If sheet does not exist, xlswrite adds a new sheet at the end of the worksheet collection. If sheet is an index larger than the number of worksheets, xlswrite appends empty sheets until the number of worksheets in the workbook equals sheet. In either case, xlswrite generates a warning indicating that it has added a new worksheet.

xlswrite(filename, M, range) writes matrix M to a rectangular region specified by range in the first worksheet of the file filename.

Specify range using the syntax 'C1:C2', where C1 and C2 are two opposing corners that define the region to write. For example, the range 'D2:H4' represents the 3-by-5 rectangular region between the two corners D2 and H4 on the worksheet. The range input is not case sensitive and uses the Excel A1 reference style. (For more information on this reference style, see Excel help.) xlswrite does not recognize named ranges.

The size defined by range should fit the size of M. If range is larger than the size of M, Excel software fills the remainder of the region with #N/A. If range is smaller than the size of M, xlswrite writes only the submatrix that fits into range to the file specified by filename.

Note If you specify only three inputs, xlswrite must decide whether the third input refers to a sheet or a range. To specify a range, include a colon character in the input string (such as 'D2:H4'). If you do not include a colon character (such as 'sales' or 'D2'), xlswrite interprets the third input as a value for sheet.

xlswrite(filename, M, sheet, range) writes matrix M to a rectangular region specified by range in worksheet sheet of the file filename. If you specify both sheet and range, the range can either fit the size of M or contain only the first cell (such as 'A2'). See the previous two syntax formats for further explanation of the sheet and range inputs.

status = xlswrite(filename, ...) returns the completion status
of the write operation in status. If the write completes successfully,
status is equal to logical 1 (true). Otherwise, status is logical 0
(false). Unless you specify an output parameter, xlswrite does not
display a status value in the Command Window.

[status, message] = xlswrite(filename, ...) returns any warning or error message generated by the write operation in the MATLAB structure message. The message structure has two fields:

- message String containing the text of the warning or error message
- identifier String containing the message identifier for the warning or error

xlswrite filename M sheet range is the command format for xlswrite, showing its usage with all input arguments specified. When using this format, you must specify sheet as a string (for example, Income or Sheet4). If the sheet name contains space characters, then you must place quotation marks around the string (for example, 'Income 2002').

Remarks Excel converts Inf values to 65535. MATLAB converts NaN values to empty cells.

If your system does not have Excel for Windows installed, or if the COM server (part of the typical installation of Excel for Windows) is unavailable, xlswrite:

- Writes matrix M as a text file in comma-separated value (CSV) format.
- Ignores the sheet and range arguments.
- Generates an error if the input matrix M is a cell array.

If your system has Microsoft Office 2003 software installed, but you want to create a file in an Excel 2007 format, you must install the Office 2007 Compatibility Pack.

Numeric Dates

Both Excel and MATLAB applications represent numeric dates as a number of serial days elapsed from a specific reference date. However, Excel and MATLAB use different reference dates:

xlswrite

Application	Reference Date
MATLAB	January 0, 0000
Excel for Windows	January 1, 1900
Excel for the Macintosh	January 2, 1904

For more information, see "Converting Dates" in the MATLAB Data Import and Export documentation.

Examples Example 1 – Writing Numeric Data to the Default Worksheet

Write a 7-element vector to Microsoft Excel file testdata.xls. By default, xlswrite writes the data to cells A1 through G1 in the first worksheet in the file:

xlswrite('testdata.xls', [12.7 5.02 -98 63.9 0 -.2 56])

Example 2 – Writing Mixed Data to a Specific Worksheet

This example writes the following mixed text and numeric data to the file tempdata.xls:

```
d = {'Time', 'Temp'; 12 98; 13 99; 14 97};
```

Call xlswrite, specifying the worksheet labeled Temperatures, and the region within the worksheet to write the data to. xlswrite writes the 4-by-2 matrix to the rectangular region that starts at cell E1 in its upper left corner:

```
s = xlswrite('tempdata.xls', d, 'Temperatures', 'E1')
s =
1
```

The output status s shows that the write operation succeeded. The data appears as shown here in the output file:

ime	Temp
12	98
13	99

14 97

Example 3 – Appending a New Worksheet to the File

Now write the same data to a worksheet that doesn't yet exist in tempdata.xls. In this case, xlswrite appends a new sheet to the workbook, calling it by the name you supplied in the sheets input argument, 'NewTemp'. xlswrite displays a warning indicating that it has added a new worksheet to the file:

xlswrite('tempdata.xls', d, 'NewTemp', 'E1')
Warning: Added specified worksheet.

If you don't want to see these warnings, you can turn them off with this command:

warning off MATLAB:xlswrite:AddSheet

Now try the write command again, this time creating another new worksheet, NewTemp2. Although the message does not appear this time, you can still retrieve it and its identifier from the second output argument, msg:

```
[stat msg] = xlswrite('tempdata.xls', d, 'NewTemp2', 'E1');
msg
msg =
    message: 'Added specified worksheet.'
    identifier: 'MATLAB:xlswrite:AddSheet'
See Also xlsread | xlsfinfo
```

How To • "Formatting Cells in Excel Files"

xmlread

Purpose	Parse XML document and return Document Object Model node	
Syntax	DOMnode = xmlread(filename)	
Description	DOMnode = xmlread(filename) reads a URL or filename and returns a Document Object Model node representing the parsed document. The filename input is a string enclosed in single quotes. The node can be manipulated by using standard DOM functions.	
	A properly parsed document displays to the screen as	
	<pre>xDoc = xmlread() xDoc = [#document: null]</pre>	
Remarks	Find out more about the Document Object Model at the World Wide Web Consortium (W3C [®]) Web site, http://www.w3.org/DOM/.	
Examples	Example 1	
	All XML files have a single root element. Some XML files declare a preferred schema file as an attribute of this element. Use the getAttribute method of the DOM node to get the name of the preferred schema file:	
	<pre>xDoc = xmlread(fullfile(matlabroot,</pre>	
	<pre>'toolbox/matlab/general/info.xml'));</pre>	
	<pre>xRoot = xDoc.getDocumentElement;</pre>	
	<pre>schemaURL = char(xRoot.getAttribute('xsi:noNamespaceSchemaLocation'))</pre>	
	<pre>schemaURL = http://www.mathworks.com/namespace/info/v1/info.xsd</pre>	

Example 2

Each info.xml file on the MATLAB path contains several listitem elements with a label and callback element. This script finds the callback that corresponds to the label 'Plot Tools':

```
infoLabel = 'Plot Tools';
infoCbk = '';
itemFound = false;
xDoc = xmlread(fullfile(matlabroot, ...
               'toolbox/matlab/general/info.xml'));
% Find a deep list of all listitem elements.
allListItems = xDoc.getElementsByTagName('listitem');
% Note that the item list index is zero-based.
for k = 0:allListItems.getLength-1
  thisListItem = allListItems.item(k);
  childNode = thisListItem.getFirstChild;
  while ~isempty(childNode)
      %Filter out text, comments, and processing instructions.
      if childNode.getNodeType == childNode.ELEMENT_NODE
         % Assume that each element has a single
         % org.w3c.dom.Text child.
         childText = char(childNode.getFirstChild.getData);
         switch char(childNode.getTagName)
         case 'label';
            itemFound = strcmp(childText, infoLabel);
         case 'callback' ;
            infoCbk = childText;
         end
      end % End IF
      childNode = childNode.getNextSibling;
   end % End WHILE
```

```
if itemFound
    break;
else
    infoCbk = '';
end
end % End FOR
disp(sprintf('Item "%s" has a callback of "%s".', ...
    infoLabel, infoCbk))
```

Example 3

This function parses an XML file using methods of the DOM node returned by xmlread, and stores the data it reads in the Name, Attributes, Data, and Children fields of a MATLAB structure:

```
function theStruct = parseXML(filename)
% PARSEXML Convert XML file to a MATLAB structure.
try
   tree = xmlread(filename);
catch
   error('Failed to read XML file %s.',filename);
end
% Recurse over child nodes. This could run into problems
% with very deeply nested trees.
trv
   theStruct = parseChildNodes(tree);
catch
   error('Unable to parse XML file %s.',filename);
end
% ----- Subfunction PARSECHILDNODES -----
function children = parseChildNodes(theNode)
% Recurse over node children.
children = [];
```

```
if theNode.hasChildNodes
```

```
childNodes = theNode.getChildNodes;
   numChildNodes = childNodes.getLength;
   allocCell = cell(1, numChildNodes);
   children = struct(
      'Name', allocCell, 'Attributes', allocCell,
                                                      . . .
      'Data', allocCell, 'Children', allocCell);
    for count = 1:numChildNodes
        theChild = childNodes.item(count-1);
        children(count) = makeStructFromNode(theChild);
    end
end
% ----- Subfunction MAKESTRUCTFROMNODE -----
function nodeStruct = makeStructFromNode(theNode)
% Create structure of node info.
nodeStruct = struct(
                                              . . .
   'Name', char(theNode.getNodeName),
   'Attributes', parseAttributes(theNode),
                                              . . .
   'Data', '',
                                              . . .
   'Children', parseChildNodes(theNode));
if any(strcmp(methods(theNode), 'getData'))
   nodeStruct.Data = char(theNode.getData);
else
   nodeStruct.Data = '';
end
% ----- Subfunction PARSEATTRIBUTES -----
function attributes = parseAttributes(theNode)
% Create attributes structure.
attributes = [];
if theNode.hasAttributes
   theAttributes = theNode.getAttributes;
```

xmlread

```
numAttributes = theAttributes.getLength;
allocCell = cell(1, numAttributes);
attributes = struct('Name', allocCell, 'Value', ...
allocCell);
for count = 1:numAttributes
attrib = theAttributes.item(count-1);
attributes(count).Name = char(attrib.getName);
attributes(count).Value = char(attrib.getValue);
end
end
```

See Also

xmlwrite, xslt

Purpose	Serialize XML Document Object Model node
Syntax	<pre>xmlwrite(filename, DOMnode) str = xmlwrite(DOMnode)</pre>
Description	<pre>xmlwrite(filename, DOMnode) serializes the Document Object Model node DOMnode to the file specified by filename. The filename input is a string enclosed in single quotes.</pre>
	<pre>str = xmlwrite(DOMnode) serializes the Document Object Model node DOMnode and returns the node tree as a string, str.</pre>
Remarks	Find out more about the Document Object Model at the World Wide Web Consortium (W3C) Web site, http://www.w3.org/DOM/.
Example	<pre>% Create a sample XML document. docNode = com.mathworks.xml.XMLUtils.createDocument ('root_element') docRootNode = docNode.getDocumentElement; for i=1:20 thisElement = docNode.createElement('child_node'); thisElement.appendChild (docNode.createTextNode(sprintf('%i',i))); docRootNode.appendChild(thisElement); end docNode.appendChild(docNode.createComment('this is a comment')); % Save the sample XML document. xmlFileName = [tempname,'.xml']; xmlwrite(xmlFileName,docNode); edit(xmlFileName);</pre>
See Also	xmlread, xslt

.

Purpose	Logical exclusive-OR
---------	----------------------

Syntax C = xor(A, B)

Description C = xor(A, B) performs an exclusive OR operation on the corresponding elements of arrays A and B. The resulting element C(i,j,...) is logical true (1) if A(i,j,...) or B(i,j,...), but not both, is nonzero.

Α	В	С
Zero	Zero	0
Zero	Nonzero	1
Nonzero	Zero	1
Nonzero	Nonzero	0

Examples Given A = [0 0 pi eps] and B = [0 -2.4 0 1], then

C = xor(A,B) C = 0 0 1 10

To see where either \boldsymbol{A} or \boldsymbol{B} has a nonzero element and the other matrix does not,

spy(xor(A,B))

See Also all, any, find, Elementwise Logical Operators, Short-Circuit Logical Operators

Purpose	Transform XML document using XSLT engine	
Syntax	result = xslt(source, style, dest) [result,style] = xslt() xslt(,'-web')	
Description	result = xslt(source, style, dest) transforms an XML document using a stylesheet and returns the resulting document's URL. The function uses these inputs, the first of which is required:	
	• source is the filename or URL of the source XML file. source can also specify a DOM node.	
	• style is the filename or URL of an XSL stylesheet.	
	 dest is the filename or URL of the desired output document. If dest is absent or empty, the function uses a temporary filename. If dest is '-tostring', the function returns the output document as a MATLAB string. 	
	<pre>[result,style] = xslt() returns a processed stylesheet appropriate for passing to subsequent XSLT calls as style. This prevents costly repeated processing of the stylesheet.</pre>	
	<code>xslt(,'-web')</code> displays the resulting document in the Help Browser.	
Remarks	MATLAB uses the Saxon XSLT processor, version 6.5.5, which supports XSLT 1.0 expressions. For more information, see http://saxon.sourceforge.net/saxon6.5.5/	
	For additional information on writing XSL stylesheets, see the World Wide Web Consortium (W3C) web site, http://www.w3.org/Style/XSL/.	
Example	This example converts the file info.xml using the stylesheet info.xsl, writing the output to the file info.html. It launches the resulting	

HTML file in the Help Browser. MATLAB has several info.xml files that are used by the **Start** menu.

xslt info.xml info.xsl info.html -web

See Also xmlread, xmlwrite

Purpose	Create array of all zeros
Syntax	<pre>B = zeros(n) B = zeros(m,n) B = zeros([m n]) B = zeros(m,n,p,) B = zeros([m n p]) B = zeros(size(A)) zeros(m, n,,classname) zeros([m,n,],classname)</pre>
Description	B = zeros(n) returns an n-by-n matrix of zeros. An error message appears if n is not a scalar.
	B = zeros(m,n) or $B = zeros([m n])$ returns an m-by-n matrix of zeros.
	<pre>B = zeros(m,n,p,) or B = zeros([m n p]) returns an m-by-n-by-p-by array of zeros.</pre>
	Note The size inputs m, n, p, should be nonnegative integers. Negative integers are treated as 0. If any trailing dimensions are 0, output B does not include those dimensions.
	<pre>B = zeros(size(A)) returns an array the same size as A consisting of all zeros.</pre>
	<pre>zeros(m, n,,classname) or zeros([m,n,],classname) is an m-by-n-by array of zeros of data type classname. classname is a string specifying the data type of the output. classname can have the following values: 'double', 'single', 'int8', 'uint8', 'int16', 'uint16', 'int32', 'uint32', 'int64', or 'uint64'.</pre>
Example	<pre>x = zeros(2,3,'int8');</pre>

Remarks The MATLAB language does not have a dimension statement; MATLAB automatically allocates storage for matrices. Nevertheless, for large matrices, MATLAB programs may execute faster if the zeros function is used to set aside storage for a matrix whose elements are to be generated one at a time, or a row or column at a time. For example x = zeros(1,n);for i = 1:n, x(i) = i; end

See Also eye, ones, rand, randn, complex

Purpose	Compress files into zip file
Syntax	<pre>zip(zipfile,files) zip(zipfile,files,rootfolder) entrynames = zip()</pre>
Description	<pre>zip(zipfile,files) creates a zip file with the name zipfile from the list of files and folders specified in files. Folders recursively include all of their content. If files includes relative paths, the zip file also contains relative paths. The zip file does not include absolute paths.</pre>
	<i>zipfile</i> is a string specifying the name of the zip file. If <i>zipfile</i> has no extension, MATLAB appends the .zip extension.
	<i>files</i> is a string or cell array of strings containing the list of files or folders included in <i>zipfile</i> .
	Individual files that are on the MATLAB path can be specified as partial path names. Otherwise an individual file can be specified relative to the current folder or with an absolute path.
	Folders must be specified relative to the current folder or with absolute paths. On UNIX systems, folders can also start with ~/ or ~username/, which expands to the current user's home folder or the specified user's home folder, respectively. The wildcard character * can be used when specifying files or folders, except when relying on the MATLAB path to resolve a file name or partial path name.
	<pre>zip(zipfile,files,rootfolder) specifies the path for files relative to rootfolder instead of the current folder. Relative paths in the zip file reflect the relative paths in files, and do not include path information from rootfolder.</pre>
	<i>entrynames</i> = zip() returns a string cell array of the names of the files contained in <i>zipfile</i> . If <i>files</i> includes relative paths, <i>entrynames</i> also contains relative paths.

Examples Zip a File

Create a zip file of the file membrane.m, which is in the MATLAB demos folder. Save the zip file in tmwlogo.zip in the current folder.

```
file = fullfile(matlabroot, 'toolbox', 'matlab', 'demos', 'membrane.m');
zip('tmwlogo',file);
```

Run zip for the files membrane.m and logo.m and save the zip file, tmwlogo.zip, in the specified folder. The source files are on the MATLAB search path.

```
myfile = fullfile('d:','myfiles','tmwlogo.zip');
zip(myfile,{'membrane.m','logo.m'});
```

Zip Selected Files

Run zip for all .m and .mat files in the current folder to the file backup.zip:

```
zip('backup',{'*.m','*.mat'});
```

Zip a Folder

Run zip for the folder mywork, which is a subfolder of the current folder. The zip file myfiles.zip recursively includes the contents of all subfolders of mywork, and stores the relative paths.

```
zip('myfiles.zip','mywork');
```

Zip Between Folders

Run zip for the files thesis.doc and defense.ppt, which are located in d:/PhD, to the zip file thesis.zip in the folder one level up from the current folder.

```
zip('../thesis.zip',{'thesis.doc','defense.ppt'},'d:/PhD');
```

See Also gzip, gunzip, tar, untar, unzip

zoom

Purpose	Turn zooming on or off or magnify by factor
GUI Alternatives	Use the Zoom tools on the figure toolbar to zoom in or zoom out on a plot, or select Zoom In or Zoom Out from the figure's Tools menu. For details, see "Enlarging the View" in the MATLAB Graphics documentation.
Syntax (1997)	<pre>Z00m on zoom off zoom out zoom reset zoom Zoom xon zoom yon zoom(factor) zoom(fig, option) h = zoom(figure_handle)</pre>
Description	 zoom on turns on interactive zooming. When interactive zooming is enabled in a figure, pressing a mouse button while your cursor is within an axes zooms into the point or out from the point beneath the mouse. Zooming changes the axes limits. When using zoom mode, you Zoom in by positioning the mouse cursor where you want the center of the plot to be and either Press the mouse button or Rotate the mouse scroll wheel away from you (upward). Zoom out by positioning the mouse cursor where you want the center of the plot to be and either Simultaneously press Shift and the mouse button, or Rotate the mouse scroll wheel toward you (downward).

Clicking and dragging over an axes when zooming in is enabled draws a rubberband box. When you release the mouse button, the axes zoom in to the region enclosed by the rubberband box.

Double-clicking over an axes returns the axes to its initial zoom setting in both zoom-in and zoom-out modes.

zoom off turns interactive zooming off.

zoom out returns the plot to its initial zoom setting.

zoom reset remembers the current zoom setting as the initial zoom setting. Later calls to zoom out, or double-clicks when interactive zoom mode is enabled, will return to this zoom level.

zoom toggles the interactive zoom status between off and on (restoring the most recently used zoom tool).

zoom xon and zoom yon set zoom on for the *x*- and *y*-axis, respectively.

zoom(factor) zooms in or out by the specified zoom factor, without affecting the interactive zoom mode. Values greater than 1 zoom in by that amount, while numbers greater than 0 and less than 1 zoom out by 1/factor.

zoom(fig, option) Any of the preceding options can be specified on a figure other than the current figure using this syntax.

h = zoom(figure_handle) returns a zoom *mode object* for the figure figure_handle for you to customize the mode's behavior.

Using Zoom Mode Objects

Access the following properties of zoom mode objects via get and modify some of them using set.

- Enable 'on'|'off' Specifies whether this figure mode is currently enabled on the figure
- FigureHandle <handle> The associated figure handle, a read-only property that cannot be set

- *Motion* 'horizontal'|'vertical'|'both' The type of zooming enabled for the figure
- Direction 'in'|'out' The direction of the zoom operation
- *RightClickAction* 'InverseZoom'|'PostContextMenu' The behavior of a right-click action

A value of 'InverseZoom' causes a right-click to zoom out. A value of 'PostContextMenu' displays a context menu. This setting persists between MATLAB sessions.

• UIContextMenu <handle> — Specifies a custom context menu to be displayed during a right-click action

This property is ignored if the RightClickAction property has been set to 'on'.

Zoom Mode Callbacks

You can program the following callbacks for zoom mode operations.

• ButtonDownFilter <function_handle> — Function to intercept ButtonDown events

The application can inhibit the zoom operation under circumstances the programmer defines, depending on what the callback returns. The input function handle should reference a function with two implicit arguments (similar to Handle Graphics object callbacks), as follows:

```
function [res] = myfunction(obj,event_obj)
% obj handle to the object that has been clicked on
% event_obj struct for event data (empty in this release)
% res [output] a logical flag to determine whether the zoom
% operation should take place or the 'ButtonDownFcn'
% property of the object should take precedence
```

• ActionPreCallback <function_handle> — Function to execute before zooming

Set this callback if you want to execute code when a zoom operation starts. The input function handle should reference a function with two implicit arguments (similar to Handle Graphics object callbacks), as follows:

function myfunction(obj,event_obj)
% obj handle to the figure that has been clicked on.
% event_obj object containing struct of event data

The event data has the following field.

Axes	The handle of the axes that is
	being zoomed

 ActionPostCallback <function_handle> — Function to execute after zooming

Set this callback if you want to execute code when a zoom operation finishes. The input function handle should reference a function with two implicit arguments (similar to Handle Graphics object callbacks), as follows:

function myfunction(obj,event_obj)
% obj handle to the figure that has been clicked on
% event_obj object containing struct of event data (same as the
% event data of the 'ActionPreCallback' callback)

Zoom Mode Utility Functions

The following functions in zoom mode query and set certain of its properties.

• flags = isAllowAxesZoom(h,axes) — Function querying permission to zoom axes

Calling the function isAllowAxesZoom on the zoom object, h, with a vector of axes handles, axes, as input returns a logical array of the

same dimension as the axes handle vector, which indicates whether a zoom operation is permitted on the axes objects.

setAllowAxesZoom(h,axes,flag) — Function to set permission to zoom axes

Calling the function setAllowAxesZoom on the zoom object, h, with a vector of axes handles, axes, and a logical scalar, flag, either allows or disallows a zoom operation on the axes objects.

• *info* = getAxesZoomMotion(h,axes) — Function to get style of zoom operations

Calling the function getAxesZoomMotion on the zoom object, H, with a vector of axes handles, axes, as input returns a character cell array of the same dimension as the axes handle vector, which indicates the type of zoom operation for each axes. Possible values for the type of operation are 'horizontal', 'vertical', or 'both'.

setAxesZoomMotion(h,axes,style) — Function to set style of zoom operations

Calling the function setAxesZoomMotion on the zoom object, h, with a vector of axes handles, axes, and a character array, style, ses the style of zooming on each axes.

Examples Example 1 – Entering Zoom Mode

Plot a graph and turn on Zoom mode:

plot(1:10); zoom on % zoom in on the plot

Example 2 – Constrained Zoom

Create zoom mode object and constrain to *x*-axis zooming:

```
plot(1:10);
h = zoom;
set(h,'Motion','horizontal','Enable','on');
```

% zoom in on the plot in the horizontal direction.

Example 3 – Constrained Zoom in Subplots

Create four axes as subplots and set zoom style differently for each by setting a different property for each axes handle:

```
ax1 = subplot(2,2,1);
plot(1:10);
h = zoom;
ax2 = subplot(2,2,2);
plot(rand(3));
setAllowAxesZoom(h,ax2,false);
ax3 = subplot(2,2,3);
plot(peaks);
setAxesZoomMotion(h,ax3,'horizontal');
ax4 = subplot(2,2,4);
contour(peaks);
setAxesZoomMotion(h,ax4,'vertical');
% Zoom in on the plots.
```

Example 4 – Coding a ButtonDown Callback

Create a buttonDown callback for zoom mode objects to trigger. Copy the following code to a new file, execute it, and observe zooming behavior:

```
function demo
% Allow a line to have its own 'ButtonDownFcn' callback.
hLine = plot(rand(1,10));
set(hLine,'ButtonDownFcn','disp(''This executes'')');
set(hLine,'Tag','DoNotIgnore');
h = zoom;
set(h,'ButtonDownFilter',@mycallback);
set(h,'Enable','on');
% mouse click on the line
%
```

```
function [flag] = mycallback(obj,event_obj)
% If the tag of the object is 'DoNotIgnore', then return true.
objTag = get(obj,'Tag');
if strcmpi(objTag,'DoNotIgnore')
    flag = true;
else
    flag = false;
end
```

Example 5 – Coding Pre- and Post-Callback Behavior

Create callbacks for pre- and post-buttonDown events for zoom mode objects to trigger. Copy the following code to a new file, execute it, and observe zoom behavior:

```
function demo
% Listen to zoom events
plot(1:10);
h = zoom;
set(h, 'ActionPreCallback',@myprecallback);
set(h, 'ActionPostCallback',@mypostcallback);
set(h, 'Enable', 'on');
%
function myprecallback(obj,evd)
disp('A zoom is about to occur.');
%
function mypostcallback(obj,evd)
newLim = get(evd.Axes, 'XLim');
msgbox(sprintf('The new X-Limits are [%.2f %.2f].',newLim));
```

Example 6 – Creating a Context Menu for Zoom Mode

Coding a context menu that lets the user to switch to Pan mode by right-clicking:

```
figure;plot(magic(10))
hCMZ = uicontextmenu;
```

```
hZMenu = uimenu('Parent', hCMZ, 'Label', 'Switch to pan', 'Callback', 'p
                       hZoom = zoom(gcf);
                       set(hZoom, 'UIContextMenu', hCMZ);
                       zoom('on')
                    You cannot add items to the built-in zoom context menu, but you can
                    replace it with your own.
Remarks
                    zoom changes the axes limits by a factor of 2 (in or out) each time you
                    press the mouse button while the cursor is within an axes. You can
                    also click and drag the mouse to define a zoom area, or double-click
                    to return to the initial zoom level.
                    You can create a zoom mode object once and use it to customize the
                    behavior of different axes, as Example 3 illustrates. You can also
                    change its callback functions on the fly.
                    Note Do not change figure callbacks within an interactive
                    mode. While a mode is active (when panning, zooming, etc.), you will
                    receive a warning if you attempt to change any of the figure's callbacks
                    and the operation will not succeed. The one exception to this rule is the
                    figure WindowButtonMotionFcn callback, which can be changed from
                    within a mode. Therefore, if you are creating a GUI that updates a
                    figure's callbacks, the GUI should some keep track of which interactive
                    mode is active, if any, before attempting to do this.
                    When you assign different zoom behaviors to different subplot axes
                    via a mode object and then link them using the linkaxes function,
                    the behavior of the axes you manipulate with the mouse carries over
                    to the linked axes, regardless of the behavior you previously set for
                    the other axes.
See Also
                    linkaxes, pan, rotate3d
                    "Object Manipulation" on page 1-110 for related functions
```

zoom

Index

Symbols and Numerics

2-44 & 2-56 2-63 * 2-44 + 2-44 - 2-44 / 2-44 : 2-70 < 2-54 > 2-54 @ 2-1618 $\searrow 2-44$ ^ 2-44 | 2-56 2-63~ 2-56 2-63 && 2-63 == 2.541) 2-68|| 2-63~= 2-54 1-norm 2-2769 2-3238 2-norm (estimate of) 2-2771

A

abs 2-73 absolute accuracy BVP 2-473 DDE 2-1083 ODE 2-2820 absolute value 2-73 Accelerator Uimenu property 2-4164 accumarray 2-74 accuracy of linear equation solution 2-869 acos 2-81 acosd 2-83 acosh 2-84 acot 2-86 acotd 2-88acoth 2-89 acsc 2-91 acscd 2-93 acsch 2-94activelegend 2-3028 actxcontrol 2-96 actxserver 2-107 Adams-Bashforth-Moulton ODE solver 2-2809 addCause, MException method 2-111 addevent 2-114addframe AVI files 2-116 addition (arithmetic operator) 2-44 addlistener 2-118 addOptional method of inputParser object 2-120 addParamValue method of inputParser object 2-123 addpath 2-126 addpref function 2-128 addprop dynamicprops method 2-129 addRequired method of inputParser object 2-132 addressing selected array elements 2-70 addsample 2-135 addsampletocollection 2-137 addtodate 2-139 addts 2-141 adjacency graph 2-1189 airy 2-143 Airy functions relationship to modified Bessel functions 2-143 align function 2-145 aligning scattered data multi-dimensional 2-2682 ALim, Axes property 2-293 all 2-151

allchild function 2-153 allocation of storage (automatic) 2-4520 AlphaData image property 2-1959 surface property 2-3816 surfaceplot property 2-3839 AlphaDataMapping image property 2-1960 patch property 2-2921 surface property 2-3817 surfaceplot property 2-3839 AmbientLightColor, Axes property 2-294 AmbientStrength Patch property 2-2922 Surface property 2-3817 surfaceplot property 2-3840 amd 2-161 analytical partial derivatives (BVP) 2-474 analyzer code 2-2604 and 2-166 and (function equivalent for &) 2-60 AND, logical bit-wise 2-419 angle 2-168 annotating graphs in plot edit mode 2-3029 Annotation areaseries property 2-221 contourgroup property 2-894 errorbarseries property 2-1263 hggroup property 2-1864 hgtransform property 2-1893 image property 2-1960 line property 2-352 2-2313 lineseries property 2-2328 Patch property 2-2922 quivergroup property 2-3186 rectangle property 2-3264 scattergroup property 2-3429

stairseries property 2-3626 stemseries property 2-3660 Surface property 2-3818 surfaceplot property 2-3840 text property 2-3923 annotation function 2-169 ans 2-211 anti-diagonal 2-1811 any 2-212 arccosecant 2-91 arccosine 2-81 arccotangent 2-86 arcsecant 2-244 arctangent 2-259 four-quadrant 2-261 arguments checking number of inputs 2-2673 checking number of outputs 2-2677 number of output 2-2675 passing variable numbers of 2-4362 arguments, function number of input 2-2675 arithmetic operations, matrix and array distinguished 2-44 arithmetic operators reference 2-44 array addressing selected elements of 2-70 dimension rearrange 2-1527 displaying 2-1166 flip dimension of 2-1527 left division (arithmetic operator) 2-46 maximum elements of 2-2491 mean elements of 2-2497 median elements of 2-2500 minimum elements of 2-2576 multiplication (arithmetic operator) 2-45 of all ones 2-2841 of all zeros 2-4519

power (arithmetic operator) 2-46 product of elements 2-3103 rearrange dimension 2-1527 removing first n singleton dimensions of 2-3513 removing singleton dimensions of 2-3613 reshaping 2-3339 reverse dimension of 2-1527 right division (arithmetic operator) 2-45 shift circularly 2-774 shifting dimensions of 2-3513 size of 2-3527 sorting elements of 2-3548 structure 2-1724 2-3368 2-3496 sum of elements 2-3795 swapping dimensions of 2-2117 2-2995 transpose (arithmetic operator) 2-46 arrayfun 2-237 arrays detecting empty 2-2133 maximum size of 2-867 arrays, structure field names of 2-1403 arrowhead matrix 2-850 ASCII delimited files writing 2-1184 ASCII data converting sparse matrix after loading from 2-3562 reading 2-1180 reading from disk 2-2379 saving to disk 2-3404 ascii function 2-243 asec 2-244 asecd 2-246 asech 2-247 asinh 2-253 aspect ratio of axes 2-998 2-2957

assert 2-255 assignin 2-257 atan 2-259 atan2 2-261 atand 2-263 atanh 2-264 .au files reading 2-279 writing 2-281 audio saving in AVI format 2-282 signal conversion 2-2306 2-2656 audiodevinfo 2-266 audioplayer 2-268 audiorecorder 2-273 aufinfo 2-278 auread 2-279 AutoScale quivergroup property 2-3187 AutoScaleFactor quivergroup property 2-3187 autoselection of OpenGL 2-1441 auwrite 2-281 average of array elements 2-2497 average, running 2-1490 avi 2-282 avifile 2-282 aviinfo 2-285 aviread 2-287 axes 2-288 editing 2-3029 setting and querying data aspect ratio 2-998 setting and querying limits 2-4490 setting and querying plot box aspect ratio 2-2957 Axes creating 2-288 defining default properties 2-289 fixed-width font 2-310 property descriptions 2-293

axis 2-331 axis crossing. *See* zero of a function azimuth (spherical coordinates) 2-3578 azimuth of viewpoint 2-4381

В

BackFaceLighting Surface property 2-3819 surfaceplot property 2-3842 BackFaceLightingpatch property 2-2924 BackgroundColor annotation textbox property 2-201 Text property 2-3924 Uitable property 2-4241 BackGroundColor Uicontrol property 2-4116 badly conditioned 2-3238 balance 2-337 BarLavout barseries property 2-353 BarWidth barseries property 2-353 base to decimal conversion 2-372 base two operations conversion from decimal to binary 2-1097 logarithm 2-2400 next power of two 2-2765 base2dec 2-372BaseLine barseries property 2-353 stem property 2-3661 BaseValue areaseries property 2-222 barseries property 2-354 stem property 2-3661 beep 2-373 BeingDeleted areaseries property 2-222 barseries property 2-354

contour property 2-895 errorbar property 2-1264 group property 2-1408 2-1961 2-3926 hggroup property 2-1865 hgtransform property 2-1894 light property 2-2296 line property 2-2314 lineseries property 2-2329 quivergroup property 2-3187 rectangle property 2-3265 scatter property 2-3430 stairseries property 2-3627 stem property 2-3661 surface property 2-3819 surfaceplot property 2-3842 transform property 2-2924 Uipushtool property 2-4203 Uitable property 2-4242 Uitoggletool property 2-4272 Uitoolbar property 2-4285 bench 2-374 benchmark 2-374 **Bessel** functions first kind 2-383 modified, first kind 2-380 modified, second kind 2-386 second kind 2-389 Bessel functions, modified relationship to Airy functions 2-143 besseli 2-380 besselj 2-383 besselk 2-386 Bessel's equation (defined) 2-383 modified (defined) 2-380 bessely 2-389 beta 2-392 beta function (defined) 2-392 incomplete (defined) 2-394

natural logarithm 2-397 betainc 2-394 betaln 2-397 bicg 2-398 bicgstab 2-407 bicgstabl 2-413 BiConjugate Gradients method 2-398 BiConjugate Gradients Stabilized method 2-407 2-413bin2dec 2-416 binary data reading from disk 2-2379 saving to disk 2-3404 binary function 2-417 binary to decimal conversion 2-416 bisection search 2-1642 bit depth guerving 2-1983 bit-wise operations AND 2-419 get 2-422 OR 2-426 set bit 2-427 shift 2-428 XOR 2-430 bitand 2-419 bitcmp 2-420 bitget 2-422 bitmaps writing 2-2012 bitmax 2-424 bitor 2-426 bitset 2-427 bitshift 2-428 bitxor 2-430 blanks 2-431 removing trailing 2-1094 blkdiag 2-432 **BMP** files writing 2-2012

bold font TeX characters 2-3949 boundary value problems 2-479 box 2-433 Box, Axes property 2-295 braces, curly (special characters) 2-66 brackets (special characters) 2-66 break 2-434 breakpoints listing 2-1054 removing 2-1040 resuming execution from 2-1043 setting in code files 2-1058 browser for help 2-1850 brush 2-437 bsxfun 2-447bubble plot (scatter function) 2-3424 Buckminster Fuller 2-3893 builtin 2-450**BusyAction** areaseries property 2-222 Axes property 2-295 barseries property 2-354 contour property 2-895 errorbar property 2-1265 Figure property 2-1409 hggroup property 2-1866 hgtransform property 2-1895 Image property 2-1962 Light property 2-2297 line property 2-2315 Line property 2-2329 patch property 2-2925 quivergroup property 2-3188 rectangle property 2-3266 Root property 2-3372 scatter property 2-3431 stairseries property 2-3628 stem property 2-3662

Surface property 2-3819 surfaceplot property 2-3842 Text property 2-3926 Uicontextmenu property 2-4101 Uicontrol property 2-4117 Uimenu property 2-4165 Uipushtool property 2-4204 Uitable property 2-4242 Uitoggletool property 2-4273 Uitoolbar property 2-4285 ButtonDownFcn area series property 2-223 Axes property 2-296 barseries property 2-355 contour property 2-896 errorbar property 2-1265 Figure property 2-1409 hggroup property 2-1866 hgtransform property 2-1895 Image property 2-1962 Light property 2-2297 Line property 2-2315 lineseries property 2-2330 patch property 2-2925 quivergroup property 2-3188 rectangle property 2-3266 Root property 2-3372 scatter property 2-3431 stairseries property 2-3628 stem property 2-3662 Surface property 2-3820 surfaceplot property 2-3843 Text property 2-3927 Uicontrol property 2-4118 Uitable property 2-4243 **BVP** solver properties analytical partial derivatives 2-474 error tolerance 2-472 Jacobian matrix 2-474 mesh 2-476

singular BVPs 2-476 solution statistics 2-477 vectorization 2-473 bvp4c 2-451 bvp5c 2-462 bvpget 2-467 bvpinit 2-468 bvpset 2-471 bvpxtend 2-479

C

calendar 2-480 call history 2-3110 CallBack Uicontextmenu property 2-4102 Uicontrol property 2-4119 Uimenu property 2-4166 CallbackObject, Root property 2-3372 calllib 2-481 callSoapService 2-483 camdolly 2-485camera dollying position 2-485 moving camera and target postions 2-485 positioning to view objects 2-491 rotating around camera target 2-493 2-495 rotating around viewing axis 2-501 setting and querying position 2-497 setting and querying projection type 2-499 setting and querying target 2-502 setting and querying up vector 2-504 setting and guerving view angle 2-506 CameraPosition, Axes property 2-297 CameraPositionMode, Axes property 2-298 CameraTarget, Axes property 2-298 CameraTargetMode, Axes property 2-298 CameraUpVector, Axes property 2-298 CameraUpVectorMode, Axes property 2-299 CameraViewAngle, Axes property 2-299

CameraViewAngleMode, Axes property 2-299 camlookat 2-491 camorbit 2-493 campan 2-495 campos 2-497 camproj 2-499 camroll 2-501 camtarget 2-502 camup 2-504 camva 2-506 camzoom 2-508cart2pol 2-512 cart2sph 2-514 Cartesian coordinates 2-512 2-514 2-3041 2-3578 case 2-515 in switch statement (defined) 2-3880 lower to upper 2-4325 upper to lower 2-2412 cast 2-517 cat 2-518 catch 2-520 caxis 2-524 Cayley-Hamilton theorem 2-3061 cd 2-529 cd (ftp) function 2-534 CData Image property 2-1963 scatter property 2-3432 Surface property 2-3821 surfaceplot property 2-3844 Uicontrol property 2-4119 Uipushtool property 2-4204 Uitoggletool property 2-4273 CDataMapping Image property 2-1965 patch property 2-2927 Surface property 2-3822 surfaceplot property 2-3844 CDataMode surfaceplot property 2-3845

CDatapatch property 2-2926 CDataSource scatter property 2-3432 surfaceplot property 2-3845 cdf2rdf 2-535cdfepoch 2-537 cdfinfo 2-539 cdflib summary of capabilities 2-543 cdfread 2-715 cdfwrite 2-719 ceil 2-722 cell 2-723 cell array conversion to from numeric array 2-2779 creating 2-723 structure of, displaying 2-743 cell2mat 2-725 cell2struct 2-727 celldisp 2-736 CellEditCallback Uitable property 2-4244 cellfun 2-737 cellplot 2-743 CellSelectionCallback Uitable property 2-4246 cgs 2-746 char 2-751 characters conversion, in serial format specification string 2-1575 check boxes 2-4109 Checked, Uimenu property 2-4166 checkerboard pattern (example) 2-3328 checkin 2-752examples 2-753 options 2-752 checkout 2-755 examples 2-756 options 2-755

child functions 2-3105 Children areaseries property 2-224 Axes property 2-301 barseries property 2-356 contour property 2-896 errorbar property 2-1266 Figure property 2-1411 hggroup property 2-1867 hgtransform property 2-1896 Image property 2-1966 Light property 2-2297 Line property 2-2316 lineseries property 2-2330 patch property 2-2928 quivergroup property 2-3189 rectangle property 2-3267 Root property 2-3372 scatter property 2-3433 stairseries property 2-3629 stem property 2-3663 Surface property 2-3822 surfaceplot property 2-3846 Text property 2-3928 Uicontextmenu property 2-4102 Uicontrol property 2-4120 Uimenu property 2-4167 Uitable property 2-4246 Uitoolbar property 2-4286 chol 2-758 Cholesky factorization 2-758 (as algorithm for solving linear equations) 2-2600 lower triangular factor 2-2900 preordering for 2-850 cholinc 2-763 cholupdate 2-771 circle rectangle function 2-3259 circshift 2-774

cla 2-778 clabel 2-779 class, object. See object classes classes field names 2-1403 loaded 2-2044 clc 2-789 2-799 2-3512 clear serial port I/O 2-798 clearing Command Window 2-789 items from workspace 2-790 Java import list 2-793 clf 2-799 ClickedCallback Uipushtool property 2-4205 Uitoggletool property 2-4274 CLim, Axes property 2-301 CLimMode, Axes property 2-302 clipboard 2-800 Clipping areaseries property 2-224 Axes property 2-302 barseries property 2-356 contour property 2-897 errrobar property 2-1266 Figure property 2-1411 hggroup property 2-1867 hgtransform property 2-1896 Image property 2-1966 Light property 2-2297 Line property 2-2317 lineseries property 2-2331 quivergroup property 2-3189 rectangle property 2-3267 Root property 2-3373 scatter property 2-3433 stairseries property 2-3629 stem property 2-3663 Surface property 2-3823

surfaceplot property 2-3846 Text property 2-3928 Uicontrol property 2-4120 Uitable property 2-4246 Clippingpatch property 2-2928 clock 2-801 close 2-802 AVI files 2-805 close (ftp) function 2-806 CloseRequestFcn, Figure property 2-1411 closest point search 2-1205 closest triangle search 2-4062 closing **MATLAB 2-3177** cmapeditor 2-830 cmpermute 2-810 cmunique 2-811 code analyzer 2-2604 Code Analyzer function 2-2604 function for entire folder 2-2614 HTML report 2-2614 code files setting breakpoints 2-1058 colamd 2-814 colon operator 2-70 color quantization performed by rgb2ind 2-3356 Color annotation arrow property 2-173 annotation doublearrow property 2-177 annotation line property 2-185 annotation textbox property 2-201 Axes property 2-302 errorbar property 2-1266 Figure property 2-1414 Light property 2-2297 Line property 2-2317 lineseries property 2-2331

quivergroup property 2-3190 stairseries property 2-3630 stem property 2-3664 Text property 2-3928 textarrow property 2-191 color approximation performed by rgb2ind 2-3356 color of fonts, see also FontColor property 2-3949 colorbar 2-818 colormap 2-825 editor 2-830 Colormap, Figure property 2-1414 colormaps converting from RGB to HSV 2-3354 plotting RGB components 2-3358 rearranging colors in 2-810 removing duplicate entries in 2-811 ColorOrder, Axes property 2-302 ColorSpec 2-848 colperm 2-850ColumnEditable Uitable property 2-4247 ColumnFormat Uitable property 2-4247 ColumnName Uitable property 2-4253 ColumnWidth Uitable property 2-4253 COM object methods actxcontrol 2-96 actxserver 2-107 delete 2-1125 events 2-1302 get 2-1696 inspect 2-2060 load 2-2384 move 2-2633 propedit 2-3114 save 2-3411

set 2-3475 server methods Execute 2-1304 Feval 2-1374 combinations of n elements 2-2681 combs 2-2681 comet 2-852 comet3 2-854 comma (special characters) 2-67 command syntax 2-3898 Command Window clearing 2-789 cursor position 2-1916 get width 2-857 commandhistory 2-856 commands help for 2-1846 2-1854 system 2-3901 UNIX 2-4301 commandwindow 2-857 comments block of 2-68 common elements. See set operations, intersection compan 2-858 companion matrix 2-858 compass 2-859 CompilerConfiguration 2-2561 CompilerConfigurationDetails 2-2561 complementary error function (defined) 2-1252 scaled (defined) 2-1252 complete elliptic integral (defined) 2-1233 modulus of 2-1231 2-1233 complex 2-862 2-1950 exponential (defined) 2-1312 logarithm 2-2397 to 2-2398 numbers 2-1925 numbers, sorting 2-3548 2-3552

phase angle 2-168 See also imaginary complex conjugate 2-879 sorting pairs of 2-954 complex data creating 2-862 complex numbers, magnitude 2-73 complex Schur form 2-3448 compression lossy 2-2017 computer 2-867 computer MATLAB is running on 2-867 concatenation of arrays 2-518 cond 2-869 condeig 2-870 condest 2-871 condition number of matrix 2-869 2-3238 improving 2-337 coneplot 2-873 conj 2-879 conjugate, complex 2-879 sorting pairs of 2-954 connecting to FTP server 2-1608 containers Map 2-2157 2-2237 2-2277 2-2450 2-3323 2-3530 2-4355 context menu 2-4097 continuation $(\ldots, \text{special characters})$ 2-67 continue 2-880 continued fraction expansion 2-3232 contour and mesh plot 2-1332 filled plot 2-1324 functions 2-1320 of mathematical expression 2-1321 with surface plot 2-1353 contour3 2-885 contourc 2-889 contourf 2-891

ContourMatrix contour property 2-897 contours in slice planes 2-915 contourslice 2-915 contrast 2-919 conv 2-920 conv2 2-922 conversion base to decimal 2-372 binary to decimal 2-416 Cartesian to cylindrical 2-512 Cartesian to polar 2-512 complex diagonal to real block diagonal 2-535 cylindrical to Cartesian 2-3041 decimal number to base 2-1091 2-1096 decimal to binary 2-1097 decimal to hexadecimal 2-1098 full to sparse 2-3559 hexadecimal to decimal 2-1858 integer to string 2-2074 lowercase to uppercase 2-4325 matrix to string 2-2461 numeric array to cell array 2-2779 numeric array to logical array 2-2401 numeric array to string 2-2783 partial fraction expansion to pole-residue 2-3341 polar to Cartesian 2-3041 pole-residue to partial fraction expansion 2-3341 real to complex Schur form 2-3401 spherical to Cartesian 2-3578 string matrix to cell array 2-745 string to numeric array 2-3687 uppercase to lowercase 2-2412 vector to character string 2-751 conversion characters in serial format specification string 2-1575 convex hulls

multidimensional vizualization 2-930 two-dimensional visualization 2-928 convhull 2-928 convhulln 2-930 convn 2-932 convolution 2-920 inverse. See deconvolution two-dimensional 2-922 coordinate system and viewpoint 2-4382 coordinates Cartesian 2-512 2-514 2-3041 2-3578 cylindrical 2-512 2-514 2-3041 polar 2-512 2-514 2-3041 spherical 2-3578 coordinates. 2-512 See also conversion copyfile 2-933 copying files and folders 2-933 copvobj 2-937 corrcoef 2-939 cosecant hyperbolic 2-970 inverse 2-91 inverse hyperbolic 2-94 cosh 2-945 cosine hyperbolic 2-945 inverse 2-81 inverse hyperbolic 2-84 cot 2-947 cotangent 2-947 hyperbolic 2-950 inverse 2-86 inverse hyperbolic 2-89 cotd 2-949 coth 2-950 cov 2-952 cplxpair 2-954 cputime 2-955

create, RandStream method 2-956 createCopy method of inputParser object 2-960 CreateFcn areaseries property 2-224 Axes property 2-303 barseries property 2-356 contour property 2-898 errorbar property 2-1267 Figure property 2-1414 group property 2-1896 hggroup property 2-1867 Image property 2-1966 Light property 2-2298 Line property 2-2317 lineseries property 2-2331 patch property 2-2928 quivergroup property 2-3190 rectangle property 2-3268 Root property 2-3373 scatter property 2-3433 stairseries property 2-3630 stemseries property 2-3664 Surface property 2-3823 surfaceplot property 2-3846 Text property 2-3928 Uicontextmenu property 2-4102 Uicontrol property 2-4120 Uimenu property 2-4167 Uipushtool property 2-4205 Uitable property 2-4254 Uitoggletool property 2-4274 Uitoolbar property 2-4286 createSoapMessage 2-964 creating your own MATLAB functions 2-1615 cross 2-966 cross product 2-966 csc 2-967 cscd 2-969

csch 2-970 csvread 2-972 csvwrite 2-975 ctranspose (function equivalent for $\g) 2-50$ ctranspose (timeseries) 2-977 cubic interpolation 2-2090 2-2093 2-2096 2-2967 piecewise Hermite 2-2080 cubic spline interpolation one-dimensional 2-2080 2-2090 2-2093 2 - 2096cumprod 2-979 cumsum 2-981 cumtrapz 2-983 cumulative product 2-979 sum 2-981 curl 2-985 curly braces (special characters) 2-66 current folder 2-529 changing 2-529 See also search path CurrentAxes 2-1415 CurrentAxes, Figure property 2-1415 CurrentCharacter, Figure property 2-1416 CurrentFigure, Root property 2-3373 CurrentObject, Figure property 2-1416 CurrentPoint Axes property 2-304 Figure property 2-1417 cursor images reading 2-1998 cursor position 2-1916 Curvature, rectangle property 2-3269 curve fitting (polynomial) 2-3053 customverctrl 2-989 Cuthill-McKee ordering, reverse 2-3883 2-3893 cylinder 2-990 cylindrical coordinates 2-512 2-514 2-3041

D

dagread 2-993 daspect 2-998 data ASCII reading from disk 2-2379 ASCII, saving to disk 2-3404 binary, saving to disk 2-3404 computing 2-D stream lines 2-3697 computing 3-D stream lines 2-3699 formatted reading from files 2-1596 isosurface from volume data 2-2181 reading binary from disk 2-2379 reading from files 2-3954 reducing number of elements in 2-3284 smoothing 3-D 2-3542 Data Uitable property 2-4255 data aspect ratio of axes 2-998 data brushing different plot types 2-438 gestures for 2-443 restrictions on 2-440 data types complex 2-862 data, aligning scattered multi-dimensional 2-2682 data, ASCII converting sparse matrix after loading from 2-3562 DataAspectRatio, Axes property 2-306 DataAspectRatioMode, Axes property 2-308 datatipinfo 2-1012 date 2-1013 date and time functions 2-1245 date string format of 2-1018 date vector 2-1038 datenum 2-1014

datestr 2-1018 datevec 2-1036 dbclear 2-1040 dbcont 2-1043 dbdown 2-1044 dblguad 2-1045 dbmex 2-1047 dbquit 2-1049 dbstack 2-1051 dbstatus 2-1054 dbstep 2-1056 dbstop 2-1058 dbtype 2-1068 dbup 2-1069 DDE solver properties error tolerance 2-1082 event location 2-1088 solver output 2-1084 step size 2-1086 dde23 2-1070 ddeget 2-1075 ddephas2 output function 2-1085 ddephas3 output function 2-1085 ddeplot output function 2-1085 ddeprint output function 2-1085 ddesd 2-1076 ddeset 2-1081 deal 2-1091 deblank 2-1094 debugging changing workspace context 2-1044 changing workspace to calling file 2-1069 displaying function call stack 2-1051 files 2-3105 function 2-2236 MEX-files on UNIX 2-1047 removing breakpoints 2-1040 resuming execution from breakpoint 2-1056 setting breakpoints in 2-1058 stepping through lines 2-1056

dec2base 2-1091 2-1096 dec2bin 2-1097 dec2hex 2-1098 decic function 2-1100 decimal number to base conversion 2-1091 2 - 1096decimal point (.) (special characters) 2-67 to distinguish matrix and array operations 2-44 decomposition Dulmage-Mendelsohn 2-1188 "economy-size" 2-3872 Schur 2-3448 singular value 2-3231 2-3872 deconv 2-1102 deconvolution 2-1102 definite integral 2-3152 del operator 2-1103 del2 2-1103 Delaunay tessellation multidimensional vizualization 2-1118 delaunayn 2-1118 delete 2-1123 2-1125 serial port I/O 2-1129 timer object 2-1131 delete (ftp) function 2-1127 delete handle method 2-1128 DeleteFcn areaseries property 2-225 Axes property 2-309 barseries property 2-357 contour property 2-898 errorbar property 2-1267 Figure property 2-1418 hggroup property 2-1868 hgtransform property 2-1897 Image property 2-1966 Light property 2-2299 lineseries property 2-2332

quivergroup property 2-3190 Root property 2-3373 scatter property 2-3434 stairseries property 2-3630 stem property 2-3665 Surface property 2-3823 surfaceplot property 2-3847 Text property 2-3929 2-3932 Uicontextmenu property 2-4104 2-4121 Uimenu property 2-4169 Uipushtool property 2-4206 Uitable property 2-4256 Uitoggletool property 2-4275 Uitoolbar property 2-4288 DeleteFcn, line property 2-2318 DeleteFcn, rectangle property 2-3269 DeleteFcnpatch property 2-2929 deleting files 2-1123 items from workspace 2-790 delevent 2-1134 delimiters in ASCII files 2-1180 2-1184 delsample 2-1135 delsamplefromcollection 2-1136 demo 2-1137 demos in Command Window 2-1209 density of sparse matrix 2-2766 depdir 2-1140 dependence, linear 2-3787 dependent functions 2-3105 depfun 2-1141 derivative approximate 2-1157 polynomial 2-3050 desktop starting without 2-2477 det 2-1145 detecting

alphabetic characters 2-2161 empty arrays 2-2133 global variables 2-2148 logical arrays 2-2162 members of a set 2-2164 objects of a given class 2-2123 positive, negative, and zero array elements 2-3520 sparse matrix 2-2199 determinant of a matrix 2-1145 detrend 2-1146 detrend (timeseries) 2-1148 deval 2-1149 diag 2-1151 diagonal 2-1151 anti- 2-1811 k-th (illustration) 2-4030 main 2-1151 sparse 2-3564 dialog 2-1153 dialog box error 2-1281 help 2-1852 input 2-2049 list 2-2374 message 2-2649 print 2-3093 question 2-3173 warning 2-4418 diary 2-1155 Diary, Root property 2-3374 DiaryFile, Root property 2-3374 diff 2-1157 differences between adjacent array elements 2-1157 between sets 2-3491 differential equation solvers defining an ODE problem 2-2811 ODE boundary value problems 2-451 2-462 adjusting parameters 2-471

extracting properties 2-467 extracting properties of 2-1285 to 2-1286 2-4027 to 2-4028 forming initial guess 2-468 ODE initial value problems 2-2798 adjusting parameters of 2-2818 extracting properties of 2-2817 parabolic-elliptic PDE problems 2-2976 diffuse 2-1159 DiffuseStrength Surface property 2-3824 surfaceplot property 2-3847 DiffuseStrengthpatch property 2-2929 digamma function 2-3118 dimension statement (lack of in MATLAB) 2-4520 dimensions size of 2-3527 **Diophantine equations 2-1677** dir 2-1160 dir (ftp) function 2-1164 direct term of a partial fraction expansion 2-3341 directive %#eml 2-2606 %#ok 2-2607 directories copying 2-933 directory changing on FTP server 2-534 listing for FTP server 2-1164 making on FTP server 2-2590 directory, changing 2-529 disconnect 2-806 discontinuities, eliminating (in arrays of phase angles) 2-4321 discontinuities, plotting functions with 2-1348 discontinuous problems 2-1542 disp 2-1166 memmapfile object 2-1168 serial port I/O 2-1171

timer object 2-1172 disp, MException method 2-1169 display 2-1174 display format 2-1554 displaying output in Command Window 2-2631 DisplayName areaseries property 2-225 barseries property 2-357 contourgroup property 2-899 errorbarseries property 2-1267 hggroup property 2-1868 hgtransform property 2-1898 image property 2-1967 Line property 2-2319 lineseries property 2-2332 Patch property 2-2929 quivergroup property 2-3191 rectangle property 2-3270 scattergroup property 2-3434 stairseries property 2-3631 stemseries property 2-3665 surface property 2-3825 surfaceplot property 2-3848 text property 2-3930 distribution Gaussian 2-1252 dither 2-1176 division array, left (arithmetic operator) 2-46 array, right (arithmetic operator) 2-45 by zero 2-2037 matrix, left (arithmetic operator) 2-45 matrix, right (arithmetic operator) 2-45 of polynomials 2-1102 divisor greatest common 2-1677 dll libraries MATLAB functions calllib 2-481 libfunctions 2-2281

libfunctionsview 2-2282 libisloaded 2-2283 libpointer 2-2285 libstruct 2-2287 loadlibrary 2-2388 unloadlibrary 2-4304 dlmread 2-1180 dlmwrite 2-1184 dmperm 2-1188 Dockable, Figure property 2-1419 docsearch 2-1194 documentation displaying online 2-1850 dolly camera 2-485 dos 2-1196 UNC pathname error 2-1197 dot 2-1198 dot product 2-966 2-1198 dot-parentheses (special characters 2-67 double 2-1199 double click, detecting 2-1444 double integral numerical evaluation 2-1045 DoubleBuffer, Figure property 2-1419 downloading files from FTP server 2-2575 dragrect 2-1200 drawing shapes circles and rectangles 2-3259 DrawMode, Axes property 2-309 drawnow 2-1202 dsearchn 2-1205 Dulmage-Mendelsohn decomposition 2-1188 dynamic fields 2-67 dynamicprops class 2-1206 dynamicprops.addprop 2-129

E

echo 2-1207 Echo, Root property 2-3374 echodemo 2-1209 echoing functions 2-1207 edge finding, Sobel technique 2-924 EdgeAlpha patch property 2-2930 surface property 2-3825 surfaceplot property 2-3848 EdgeColor annotation ellipse property 2-182 annotation rectangle property 2-188 annotation textbox property 2-201 areaseries property 2-226 barseries property 2-358 patch property 2-2931 Surface property 2-3826 surfaceplot property 2-3849 Text property 2-3931 EdgeColor, rectangle property 2-3271 EdgeLighting patch property 2-2931 Surface property 2-3827 surfaceplot property 2-3850 editable text 2-4109 editing files 2-1214 eig 2-1217 eigensystem transforming 2-535 eigenvalue accuracy of 2-1217 complex 2-535 matrix logarithm and 2-2406 modern approach to computation of 2-3046 of companion matrix 2-858 problem 2-1218 2-3051 problem, generalized 2-1218 2-3051 problem, polynomial 2-3051 repeated 2-1219 Wilkinson test matrix and 2-4468

eigenvalues effect of roundoff error 2-337 improving accuracy 2-337 eigenvector left 2-1218 matrix, generalized 2-3208 right 2-1218 eigs 2-1221 elevation (spherical coordinates) 2-3578 elevation of viewpoint 2-4381 ellipj 2-1231 ellipke 2-1233 ellipsoid 2-1235 elliptic functions, Jacobian (defined) 2-1231 elliptic integral complete (defined) 2-1233 modulus of 2-1231 2-1233 else 2-1237 elseif 2-1238 %#eml 2-2606 Enable Uicontrol property 2-4122 Uimenu property 2-4169 Uipushtool property 2-4207 Uitable property 2-4256 Uitogglehtool property 2-4276 end 2-1243 end caps for isosurfaces 2-2171 end of line, indicating 2-68 eomday 2-1245 eg 2-1249 eq, MException method 2-1251 equal arrays detecting 2-2136 2-2140 equal sign (special characters) 2-66 equations, linear accuracy of solution 2-869 EraseMode areaseries property 2-226

barseries property 2-358 contour property 2-900 errorbar property 2-1268 hggroup property 2-1869 hgtransform property 2-1898 Image property 2-1968 Line property 2-2320 lineseries property 2-2333 quivergroup property 2-3192 rectangle property 2-3271 scatter property 2-3435 stairseries property 2-3632 stem property 2-3666 Surface property 2-3827 surfaceplot property 2-3850 Text property 2-3932 EraseModepatch property 2-2932 error 2-1254 roundoff. See roundoff error error function complementary 2-1252 (defined) 2-1252 scaled complementary 2-1252 error message displaying 2-1254 Index into matrix is negative or zero 2-2402 retrieving last generated 2-2243 2-2251 error messages Out of memory 2-2878 error tolerance BVP problems 2-472 DDE problems 2-1082 ODE problems 2-2819 errorbars, confidence interval 2-1259 errordlg 2-1281 ErrorMessage, Root property 2-3374 errors MException class 2-1251 addCause 2-111 constructor 2-2567

disp 2-1169 eq 2-1251 getReport 2-1741 isegual 2-2139 last 2-2240 ne 2-2689 rethrow 2-3348 throw 2-3980 throwAsCaller 2-3984 ErrorType, Root property 2-3375 etime 2-1284 etree 2-1285 etreeplot 2-1286 eval 2-1287 evalc 2-1290 evalin 2-1291 event location (DDE) 2-1088 event location (ODE) 2-2826 event.EventData 2-1293 event.listener 2-1294 event.PropertyEvent 2-1296 event.proplistener 2-1297 events 2-1302 examples calculating isosurface normals 2-2178 contouring mathematical expressions 2-1321 isosurface end caps 2-2171 isosurfaces 2-2182 mesh plot of mathematical function 2-1330 mesh/contour plot 2-1334 plotting filled contours 2-1325 plotting function of two variables 2-1338 plotting parametric curves 2-1341 polar plot of function 2-1344 reducing number of patch faces 2-3281 reducing volume data 2-3284 subsampling volume data 2-3792 surface plot of mathematical function 2-1348 surface/contour plot 2-1355 Excel spreadsheets

loading 2-4495 exclamation point (special characters) 2-68 Execute 2-1304 executing statements repeatedly 2-1552 2-4455 executing statements repeatedly in parallel 2-2894 execution improving speed of by setting aside storage 2-4520 pausing function 2-2955 resuming from breakpoint 2-1043 time for files 2-3105 exifread 2-1306 exist 2-1307 exit 2-1311 expint 2-1313 expm 2-1314 expm1 2-1316 exponential 2-1312 complex (defined) 2-1312 integral 2-1313 matrix 2-1314 exponentiation array (arithmetic operator) 2-46 matrix (arithmetic operator) 2-46 export2wsdlg 2-1317 extension, filename .m 2-1615 .mat 2-3404 Extent Text property 2-3934 Uicontrol property 2-4123 Uitable property 2-4257 ezcontour 2-1320 ezcontourf 2-1324 ezmesh 2-1328 ezmeshc 2-1332ezplot 2-1336 ezplot3 2-1340 ezpolar 2-1343

ezsurf 2-1346 ezsurfc 2-1353

F

F-norm 2-2769 FaceAlpha annotation textbox property 2-202 FaceAlphapatch property 2-2933 FaceAlphasurface property 2-3828 FaceAlphasurfaceplot property 2-3851 FaceColor annotation ellipse property 2-182 annotation rectangle property 2-188 areaseries property 2-228 barseries property 2-360 Surface property 2-3829 surfaceplot property 2-3852 FaceColor, rectangle property 2-3272 FaceColorpatch property 2-2934 FaceLighting Surface property 2-3829 surfaceplot property 2-3853 FaceLightingpatch property 2-2934 faces, reducing number in patches 2-3280 Faces, patch property 2-2935 FaceVertexAlphaData, patch property 2-2936 FaceVertexCData, patch property 2-2937 factor 2-1360 factorial 2-1361 factorization LU 2-2430 QZ 2-3052 2-3208 factorization, Cholesky 2-758 (as algorithm for solving linear equations) 2-2600 preordering for 2-850 factors, prime 2-1360 false 2-1362 fclose

serial port I/O 2-1364 feather 2-1366 feval 2-1372 Feval 2-1374 fft 2-1379 FFT. See Fourier transform fft2 2-1384 fftn 2-1385 fftshift 2-1387 fftw 2-1390 FFTW 2-1382 fgetl serial port I/O 2-1396 fgets serial port I/O 2-1400 field names of a structure, obtaining 2-1403 fieldnames 2-1403 fields, of structures dynamic 2-67 figure 2-1405 Figure creating 2-1405 defining default properties 2-1407 properties 2-1408 redrawing 2-3287 figure windows moving in front of MATLAB® desktop 2-3512 figure windows, displaying 2-1503 figurepalette 2-1463 figures annotating 2-3029 saving 2-3415 Figures updating from file 2-1202 file extension, getting 2-1479 modification date 2-1160 file formats getting list of supported formats 2-1985 reading 2-993 2-1996

writing 2-2010 file name building from parts 2-1611 file size querying 2-1983 fileattrib 2-1465 filebrowser 2-1472 filemarker 2-1477 filename parts 2-1479 temporary 2-3912 filename extension .m 2-1615 .mat 2-3404 fileparts 2-1479 files ASCII delimited reading 2-1180 writing 2-1184 checking existence of 2-1307 checking for problems 2-2604 contents, listing 2-4069 copying 2-933 copying with copyfile 2-933 cyclomatic complexity of 2-2604 debugging with profile 2-3105 deleting 2-1123 deleting on FTP server 2-1127 editing 2-1214 Excel spreadsheets loading 2-4495 fig 2-3415 figure, saving 2-3415 line numbers, listing 2-1068 lint tool 2-2604 listing 2-1160 in folder 2-4447 listing contents of 2-4069 locating 2-4452 McCabe complexity of 2-2604

mdl 2-3415 model, saving 2-3415 opening in Web browser 2-4440 opening in Windows applications 2-4469 optimizing 2-3105 path, getting 2-1479 pathname for 2-4452 problems, checking for 2-2604 reading data from 2-3954 formatted 2-1596 reading data from 2-993 reading image data from 2-1996 size, determining 2-1162 sound reading 2-279 2-4432 writing 2-281 to 2-282 2-4438 startup 2-2469 .wav reading 2-4432 writing 2-4438 WK1 loading 2-4474 writing to 2-4477 writing image data to 2-2010 filesep 2-1482 fill 2-1483 Fill contour property 2-901 fill3 2-1486 filter 2-1489 digital 2-1489 finite impulse response (FIR) 2-1489 infinite impulse response (IIR) 2-1489 two-dimensional 2-922 filter (timeseries) 2-1492 filter2 2-1495 find 2-1497 findall function 2-1502

findfigs 2-1503 finding 2-1497 sign of array elements 2-3520 zero of a function 2-1638 See also detecting findobj 2-1504 findobj handle method 2-1508 findprop handle method 2-1509 findstr 2-1511 finish 2-1512 finish.m 2-3177 FIR filter 2-1489 FitBoxToText, annotation textbox property 2-202 FitHeightToText annotation textbox property 2-202 fitsinfo 2-1514 fitsread 2-1523 fix 2-1526 fixed-width font axes 2-310 text 2-3935 uicontrols 2-4124 uitables 2-4258 FixedColors, Figure property 2-1420 FixedWidthFontName, Root property 2-3374 flints 2-2656 flip array dimension 2-1527 flip array along dimension 2-1527 flip matrix on horizontal axis 2-1529 on vertical axis 2-1528 flipdim 2-1527 fliplr 2-1528 flipud 2-1529 floating-point integer, maximum 2-424 floating-point arithmetic, IEEE

smallest postive number 2-3252 floor 2-1531 flow control break 2-434 case 2-515 end 2-1243 error 2-1256 for 2-1552 keyboard 2-2236 otherwise 2-2877 parfor 2-2894 return 2-3352 switch 2-3880 while 2-4455 fminbnd 2-1533 fminsearch 2-1538 folder listing MATLAB files in 2-4447 root 2-2470 temporary system 2-3911 folders adding to search path 2-126 checking existence of 2-1307 copying 2-933 creating 2-2587 listing 2-2414 listing contents of 2-1160 removing 2-3364 removing from search path 2-3369 font fixed-width, axes 2-310 fixed-width, text 2-3935 fixed-width, uicontrols 2-4124 fixed-width, uitables 2-4258 FontAngle annotation textbox property 2-204 Axes property 2-310 Text property 2-192 2-3934 Uicontrol property 2-4124

Uitable property 2-4258 FontName annotation textbox property 2-204 Axes property 2-310 Text property 2-3934 textarrow property 2-192 Uicontrol property 2-4124 Uitable property 2-4258 fonts bold 2-192 2-205 2-3935 italic 2-192 2-204 2-3934 specifying size 2-3935 **TeX** characters bold 2-3949 italics 2-3949 specifying family 2-3949 specifying size 2-3949 units 2-192 2-205 2-3935 FontSize annotation textbox property 2-205 Axes property 2-311 Text property 2-3935 textarrow property 2-192 Uicontrol property 2-4125 Uitable property 2-4259 FontUnits Axes property 2-311 Text property 2-3935 Uicontrol property 2-4125 Uitable property 2-4259 FontWeight annotation textbox property 2-205 Axes property 2-311 Text property 2-3935 textarrow property 2-192 Uicontrol property 2-4125 Uitable property 2-4259 fopen serial port I/O 2-1550 for 2-1552

ForegroundColor Uicontrol property 2-4126 Uimenu property 2-4169 Uitable property 2-4260 format 2-1554 Format 2-3375 FormatSpacing, Root property 2-3376 formatted data reading from file 2-1596 Fourier transform algorithm, optimal performance of 2-1382 2-1936 2-1938 2-2765 as method of interpolation 2-2095 discrete, n-dimensional 2-1385 discrete, one-dimensional 2-1379 discrete, two-dimensional 2-1384 fast 2-1379 inverse, n-dimensional 2-1940 inverse, one-dimensional 2-1936 inverse, two-dimensional 2-1938 shifting the zero-frequency component of 2-1388 fplot 2-1562 2-1579 fprintf serial port I/O 2-1575 fraction, continued 2-3232 fragmented memory 2-2878 frame2im 2-1579 frames 2-4109 fread serial port I/O 2-1588 freqspace 2-1594 frequency response desired response matrix frequency spacing 2-1594 frequency vector 2-2409 fromName meta.class method 2-2531 fromName meta.package method 2-2542 fscanf serial port I/O 2-1601

FTP

connecting to server 2-1608 ftp function 2-1608 full 2-1610 fullfile 2-1611 func2str 2-1613 function 2-1615declaration 2-1615 echoing commands 2-1207 naming conventions 2-1615 function handle 2-1618 function handles overview of 2-1618 function syntax 2-3898 functions 2-1621 call history 2-3110 call stack for 2-1051 checking existence of 2-1307 clearing from workspace 2-790 debugging 2-2236 finding using keywords 2-2410 help for 2-1846 2-1854 in memory 2-2044 locating 2-4452 locking (preventing clearing) 2-2617 pathname for 2-4452 pausing execution of 2-2955 programming 2-1615 that work down the first non-singleton dimension 2-3513 unlocking (allowing clearing) 2-2668 funm 2-1625 fwrite serial port I/O 2-1634 fzero 2-1638

G

gallery 2-1644 gamma function

(defined) 2-1671 incomplete 2-1671 logarithm of 2-1671 logarithmic derivative 2-3118 Gauss-Kronrod quadrature 2-3165 Gaussian distribution function 2-1252 Gaussian elimination (as algorithm for solving linear equations) 2-2110 2-2601 Gauss Jordan elimination with partial pivoting 2-3399 LU factorization 2-2430 gca 2-1674 gcbf function 2-1675 gcbo function 2-1676 gcd 2-1677 gcf 2-1679 gco 2-1680 ge 2-1681 generalized eigenvalue problem 2-1218 2-3051 generating a sequence of matrix names (M1 through M12) 2-1288 genpath 2-1683 genvarname 2-1685 geodesic dome 2-3893 get 2-1689 2-1696 memmapfile object 2-1699 serial port I/O 2-1705 timer object 2-1707 get (timeseries) 2-1709 get (tscollection) 2-1710 get hgsetget class method 2-1698 get, RandStream method 2-1704 getabstime (timeseries) 2-1711 getabstime (tscollection) 2-1713 getAllPackages meta.package method 2-2543 getappdata function 2-1715 getCompilerConfigurations 2-2561 getdatasamplesize 2-1720 getDefaultStream, RandStream method 2-1721 getdisp hgsetget class method 2-1722 getenv 2-1723 getframe 2-1729 image resolution and 2-1730 getinterpmethod 2-1735 getpixelposition 2-1736 getpref function 2-1738 getgualitydesc 2-1740 getReport, MException method 2-1741 getsampleusingtime (timeseries) 2-1744 getsampleusingtime (tscollection) 2-1745 gettimeseriesnames 2-1748 gettsafteratevent 2-1749 gettsafterevent 2-1750 gettsatevent 2-1751 gettsbeforeatevent 2-1752 gettsbeforeevent 2-1753 gettsbetweenevents 2-1754GIF files writing 2-2012 ginput function 2-1760 global 2-1763 global variable defining 2-1763 global variables, clearing from workspace 2-790 gmres 2-1765 golden section search 2-1536 Goup defining default properties 2-1892 gplot 2-1771 grabcode function 2-1773 gradient 2-1775 gradient, numerical 2-1775 graph adjacency 2-1189 graph theory 2-4305 graphics objects Axes 2-288 Figure 2-1405 getting properties 2-1689

Image 2-1951 Light 2-2294 Line 2-2307 Patch 2-2901 resetting properties 2-3336 Root 2-3371 setting properties 2-3467 Surface 2-3811 Text 2-3918 uicontextmenu 2-4097 Uicontrol 2-4108 Uimenu 2-4161 graphics objects, deleting 2-1123 graphs editing 2-3029 graymon 2-1778 greatest common divisor 2-1677 Greek letters and mathematical symbols 2-196 2-207 2-3947 grid 2-1779 grid arrays for volumetric plots 2-2525 multi-dimensional 2-2682 griddatan 2-1786 GridLineStyle, Axes property 2-312 group hggroup function 2-1861 asvd 2-1788 at 2-1794 gtext 2-1796 guidata function 2-1797 GUIDE object methods inspect 2-2060 guihandles function 2-1802 GUIs, printing 2-3088 gunzip 2-1803 gzip 2-1805

Η

hadamard 2-1806 Hadamard matrix 2-1806 subspaces of 2-3787 handle class 2-1807 handle graphics hgtransform 2-1881 handle graphicshggroup 2-1861 handle relational operators 2-3320 handle.addlistener 2-118 handle.delete 2-1128 handle.findobj 2-1508 handle.findprop 2-1509 handle.isvalid 2-2209 handle.notify 2-2774 HandleVisibility areaseries property 2-228 Axes property 2-312 barseries property 2-360 contour property 2-901 errorbar property 2-1269 Figure property 2-1421 hggroup property 2-1871 hgtransform property 2-1900 Image property 2-1969 Light property 2-2299 Line property 2-2321 lineseries property 2-2334 patch property 2-2938 quivergroup property 2-3193 rectangle property 2-3272 Root property 2-3376 stairseries property 2-3633 stem property 2-3667 Surface property 2-3830 surfaceplot property 2-3853 Text property 2-3936 Uicontextmenu property 2-4104 Uicontrol property 2-4126 Uimenu property 2-4170

Uipushtool property 2-4207 Uitable property 2-4260 Uitoggletool property 2-4277 Uitoolbar property 2-4288 hankel 2-1811 Hankel matrix 2-1811 HDF appending to when saving (WriteMode) 2-2016 compression 2-2016 setting JPEG quality when writing 2-2016 HDF files writing images 2-2012 HDF4 summary of capabilities 2-1812 HDF5 high-level access 2-1814 summary of capabilities 2-1814 HDF5 class low-level access 2-1814 hdf5info 2-1817 hdf5read 2-1819 hdf5write 2-1821 hdfinfo 2-1825 hdfread 2-1833 hdftool 2-1845 Head1Length annotation doublearrow property 2-177 Head1Style annotation doublearrow property 2-178 Head1Width annotation doublearrow property 2-179 Head2Length annotation doublearrow property 2-177 Head2Style annotation doublearrow property 2-178 Head2Width annotation doublearrow property 2-179 HeadLength annotation arrow property 2-173

textarrow property 2-193 HeadStyle annotation arrow property 2-173 textarrow property 2-193 HeadWidth annotation arrow property 2-174 textarrow property 2-194 Height annotation ellipse property 2-183 help 2-1846 keyword search in functions 2-2410 online 2-1846 Help browser 2-1850 accessing from doc 2-1191 Help Window 2-1854 helpbrowser 2-1850 helpdesk 2-1851 helpdlg 2-1852 helpwin 2-1854 Hermite transformations, elementary 2-1677 hess 2-1855 Hessenberg form of a matrix 2-1855 hex2dec 2-1858 hex2num 2-1859 hgsetget class 2-1880 hgsetget.get 2-1698 hgsetget.getdisp 2-1722 hgsetget.set 2-3476 hidden 2-1905 Hierarchical Data Format (HDF) files writing images 2-2012 hilb 2-1906 Hilbert matrix 2-1906 inverse 2-2113 hist 2-1907 histc 2-1911 HitTest areaseries property 2-230 Axes property 2-313 barseries property 2-362

contour property 2-903 errorbar property 2-1271 Figure property 2-1422 hggroup property 2-1872 hgtransform property 2-1901 Image property 2-1971 Light property 2-2301 Line property 2-2322 lineseries property 2-2336 Patch property 2-2939 quivergroup property 2-3195 rectangle property 2-3274 Root property 2-3376 scatter property 2-3438 stairseries property 2-3635 stem property 2-3669 Surface property 2-3831 surfaceplot property 2-3855 Text property 2-3937 Uicontrol property 2-4127 Uipushtool property 2-4208 Uitable property 2-4261 Uitoggletool property 2-4277 Uitoolbarl property 2-4289 HitTestArea areaseries property 2-230 barseries property 2-362 contour property 2-903 errorbar property 2-1271 quivergroup property 2-3195 scatter property 2-3438 stairseries property 2-3635 stem property 2-3669 hold 2-1914 home 2-1916 HorizontalAlignment Text property 2-3938 textbox property 2-194 2-205 Uicontrol property 2-4127 horzcat 2-1917

horzcat (function equivalent for [,]) 2-68 horzcat (tscollection) 2-1919 hostid 2-1920 Householder reflections (as algorithm for solving linear equations) 2-2602 hsv2rgb 2-1921 HTML in Command Window 2-2465 HTML browser in MATLAB 2-1850 HTML files opening 2-4440 hyperbolic cosecant 2-970 cosecant, inverse 2-94 cosine 2-945 cosine, inverse 2-84 cotangent 2-950 cotangent, inverse 2-89 secant 2-3455 secant, inverse 2-247 sine 2-3525 sine, inverse 2-253 tangent 2-3907 tangent, inverse 2-264 hyperlink displaying in Command Window 2-1166 hyperlinks in Command Window 2-2465 hyperplanes, angle between 2-3787 hypot 2-1922

i 2-1925 icon images reading 2-1998 idealfilter (timeseries) 2-1926 identity matrix sparse 2-3575 idivide 2-1930 **IEEE** floating-point arithmetic smallest positive number 2-3252 if 2-1932 ifft 2-1936 ifft2 2-1938 ifftn 2-1940 ifftshift 2-1942 IIR filter 2-1489 ilu 2-1943 im2java 2-1948 imag 2-1950 image 2-1951 Image creating 2-1951 properties 2-1959 image types querying 2-1983 images file formats 2-1996 2-2010 reading data from files 2-1996 returning information about 2-1982 writing to files 2-2010 Images converting MATLAB image to Java Image 2-1948 imagesc 2-1976 imaginary 2-1950 part of complex number 2-1950 unit (sqrt(\xd0 1)) 2-1925 2-2214 See also complex imapprox 2-1980 imfinfo returning file information 2-1982 imformats 2-1985 import 2-1988 importing Java class and package names 2-1988 imread 2-1996 imwrite 2-2010

incomplete beta function (defined) 2-394 incomplete gamma function (defined) 2-1671 ind2sub 2-2033 Index into matrix is negative or zero (error message) 2-2402 indexed images converting from RGB 2-3355 indexing logical 2-2401 indices, array of sorted elements 2-3549 Inf 2-2037 infinity 2-2037 norm 2-2769 info 2-2040 information returning file information 2-1982 inline 2-2041 inmem 2-2044 inpolygon 2-2046 input 2-2048 checking number of arguments 2-2673 name of array passed as 2-2053 number of arguments 2-2675 prompting users for 2-2048 inputdlg 2-2049 inputname 2-2053 inputParser 2-2054 inspect 2-2060 installation, root folder 2-2470 instance properties 2-129 instrcallback 2-2068 instrfind 2-2069 instrfindall 2-2071 example of 2-2072 int2str 2-2074 integer floating-point, maximum 2-424

IntegerHandle Figure property 2-1422 integration polynomial 2-3057 guadrature 2-3152 2-3161 interp1 2-2079 interp1q 2-2087 interp2 2-2089 interp3 2-2093 interpft 2-2095 interpn 2-2096 interpolated shading and printing 2-3089 interpolation cubic method 2-2079 2-2089 2-2093 2-2096 cubic spline method 2-2079 2-2089 2-2093 2 - 2096FFT method 2-2095 linear method 2-2079 2-2089 2-2093 2-2096 multidimensional 2-2096 nearest neighbor method 2-2079 2-2089 2-2093 2-2096 one-dimensional 2-2079 three-dimensional 2-2093 two-dimensional 2-2089 Interpreter Text property 2-3939 textarrow property 2-194 textbox property 2-205 interpstreamspeed 2-2099 Interruptible areaseries property 2-230 Axes property 2-313 barseries property 2-362 contour property 2-903 errorbar property 2-1272 Figure property 2-1423 hggroup property 2-1872 hgtransform property 2-1901 Image property 2-1971 Light property 2-2301

Line property 2-2322 lineseries property 2-2336 patch property 2-2940 quivergroup property 2-3195 rectangle property 2-3274 Root property 2-3376 scatter property 2-3439 stairseries property 2-3635 stem property 2-3670 Surface property 2-3831 2-3855 Text property 2-3940 Uicontextmenu property 2-4105 Uicontrol property 2-4128 Uimenu property 2-4170 Uipushtool property 2-4208 Uitable property 2-4261 Uitoggletool property 2-4278 Uitoolbar property 2-4289 intersect 2-2103 intmax 2-2104 intmin 2-2105 intwarning 2-2106 inv 2-2110 inverse cosecant 2-91 cosine 2-81 cotangent 2-86 Fourier transform 2-1936 2-1938 2-1940 Hilbert matrix 2-2113 hyperbolic cosecant 2-94 hyperbolic cosine 2-84 hyperbolic cotangent 2-89 hyperbolic secant 2-247 hyperbolic sine 2-253 hyperbolic tangent 2-264 of a matrix 2-2110 secant 2-244 tangent 2-259 tangent, four-quadrant 2-261 inversion, matrix

accuracy of 2-869 InvertHardCopy, Figure property 2-1424 invhilb 2-2113 involutary matrix 2-2900 ipermute 2-2117 igr (timeseries) 2-2118 is* 2-2120 isa 2-2123 isappdata function 2-2125 iscell 2-2126 iscellstr 2-2127 ischar 2-2128 isdir 2-2130 isempty 2-2133 isempty (timeseries) 2-2134 isempty (tscollection) 2-2135 isegual 2-2136 isequal, MException method 2-2139 isequalwithequalnans 2-2140 isfield 2-2144 isfinite 2-2146 isfloat 2-2147 isglobal 2-2148 ishandle 2-2150 ishghandle 2-2151 isinf 2-2153 isinteger 2-2154 isjava 2-2156 iskeyword 2-2159 isletter 2-2161 islogical 2-2162 ismac 2-2163 ismember 2-2164isnan 2-2167 isnumeric 2-2168 isocap 2-2171 isonormals 2-2178 isosurface 2-2181 calculate data from volume 2-2181 end caps 2-2171

vertex normals 2-2178 ispc 2-2186 ispref function 2-2188 isprime 2-2189 isreal 2-2191 isscalar 2-2194 issorted 2-2195 isspace 2-2198 2-2201 issparse 2-2199 isstr 2-2200 isstruct 2-2205 isstudent 2-2206 isunix 2-2208 isvalid 2-2210 timer object 2-2211 isvalid handle method 2-2209 isvarname 2-2212 isvector 2-2213 italics font TeX characters 2-3949

J

j 2-2214 Jacobi rotations 2-3598 Jacobian elliptic functions (defined) 2-1231 Jacobian matrix (BVP) 2-474 Jacobian matrix (ODE) 2-2827 generating sparse numerically 2-2828 2 - 2830specifying 2-2828 2-2830 vectorizing ODE function 2-2828 to 2-2830 Java class names 2-793 2-1988 object methods inspect 2-2060 objects 2-2156 Java Image class creating instance of 2-1948

Java import list adding to 2-1988 clearing 2-793 Java version used by MATLAB 2-4372 java method 2-2219 2-2226 java object 2-2229 javaaddath 2-2215 javachk 2-2220 javaclasspath 2-2221 javaMethod 2-2226 javaMethodEDT 2-2228 javaObject 2-2229 javaObjectEDT 2-2231 javarmpath 2-2232 joining arrays. See concatenation Joint Photographic Experts Group (JPEG) writing 2-2012 JPEG setting Bitdepth 2-2016 specifying mode 2-2017 **JPEG 2000** setting tile size 2-2018 JPEG 2000 comment setting when writing a JPEG 2000 image 2-2017 specifying 2-2017 JPEG comment setting when writing a JPEG image 2-2016 JPEG files parameters that can be set when writing 2-2016 writing 2-2012 JPEG quality setting when writing a JPEG image 2-2017 to 2-2018 2-2022 setting when writing an HDF image 2-2016 JPEG2000 files parameters that can be set when writing 2-2017 jvm

version used by MATLAB 2-4372

Κ

K>> prompt keyboard function 2-2236 keep some variables when clearing 2-796 keyboard 2-2236 keyboard mode 2-2236 terminating 2-3352 **KeyPressFcn** Uicontrol property 2-4129 Uitable property 2-4262 KeyPressFcn, Figure property 2-1424 KevReleaseFcn, Figure property 2-1426 keyword search in functions 2-2410 keywords iskeyword function 2-2159 kron 2-2238 Kronecker tensor product 2-2238 Krylov subspaces 2-3977

L

Label, Uimenu property 2-4172 labeling axes 2-4488 matrix columns 2-1166 plots (with numeric values) 2-2783 LabelSpacing contour property 2-904 Laplacian 2-1103 Laplacian matrix 2-4305 largest array elements 2-2491 last, MException method 2-2240 lasterr 2-2243 lasterror 2-2246 lastwarn 2-2251 LaTeX, see TeX 2-196 2-207 2-3947 Layer, Axes property 2-314 Layout Editor starting 2-1801 lcm 2-2253 LData errorbar property 2-1272 LDataSource errorbar property 2-1272 ldivide (function equivalent for .) 2-49le 2-2261 least common multiple 2-2253 least squares polynomial curve fitting 2-3053 problem, overdetermined 2-3004 legend 2-2263 properties 2-2269 setting text properties 2-2269 legendre 2-2272 Legendre functions (defined) 2-2272 Schmidt semi-normalized 2-2272 length serial port I/O 2-2278 length (timeseries) 2-2279 length (tscollection) 2-2280 LevelList contour property 2-904 LevelListMode contour property 2-904 LevelStep contour property 2-905 LevelStepMode contour property 2-905 libfunctions 2-2281 libfunctionsview 2-2282 libisloaded 2-2283 libpointer 2-2285 libstruct 2-2287 license 2-2290 light 2-2294

Light creating 2-2294 defining default properties 2-1957 2-2295 properties 2-2296 Light object positioning in spherical coordinates 2-2304 lightangle 2-2304 lighting 2-2305 limits of axes, setting and querying 2-4490 line 2-2307 editing 2-3029 Line creating 2-2307 defining default properties 2-2312 properties 2-2313 2-2328 line numbers in files 2-1068 linear audio signal 2-2306 2-2656 linear dependence (of data) 2-3787 linear equation systems accuracy of solution 2-869 linear equation systems, methods for solving Cholesky factorization 2-2600 Gaussian elimination 2-2601 Householder reflections 2-2602 matrix inversion (inaccuracy of) 2-2110 linear interpolation 2-2079 2-2089 2-2093 2-2096 linear regression 2-3053 linearly spaced vectors, creating 2-2370 LineColor contour property 2-905 lines computing 2-D stream 2-3697 computing 3-D stream 2-3699 drawing stream lines 2-3701 LineSpec 2-2345 LineStyle annotation arrow property 2-174 annotation doublearrow property 2-179 annotation ellipse property 2-183 annotation line property 2-185

annotation rectangle property 2-189 annotation textbox property 2-206 areaseries property 2-231 barseries property 2-363 contour property 2-906 errorbar property 2-1273 Line property 2-2323 lineseries property 2-2337 patch property 2-2940 quivergroup property 2-3196 rectangle property 2-3274 stairseries property 2-3636 stem property 2-3670 surface object 2-3832 surfaceplot object 2-3855 text object 2-3941 textarrow property 2-195 LineStyleOrder Axes property 2-314 LineWidth annotation arrow property 2-175 annotation doublearrow property 2-180 annotation ellipse property 2-183 annotation line property 2-186 annotation rectangle property 2-189 annotation textbox property 2-206 areaseries property 2-231 Axes property 2-315 barseries property 2-363 contour property 2-906 errorbar property 2-1273 Line property 2-2323 lineseries property 2-2337 Patch property 2-2940 quivergroup property 2-3196 rectangle property 2-3274 scatter property 2-3439 stairseries property 2-3636 stem property 2-3671 Surface property 2-3832

surfaceplot property 2-3856 text object 2-3942 textarrow property 2-195 linkaxes 2-2351 linkdata 2-2355 linkprop 2-2363 links in Command Window 2-2465 linsolve 2-2367 linspace 2-2370 lint tool for checking problems 2-2604 list boxes 2-4110 defining items 2-4135 list, RandStream method 2-2371 ListboxTop, Uicontrol property 2-4130 listdlg 2-2374 listfonts 2-2377 load 2-2379 2-2384 serial port I/O 2-2386 loadlibrary 2-2388 Lobatto IIIa ODE solver 2-460 2-466 local variables 2-1615 2-1763 locking functions 2-2617 log 2-2397 saving session to file 2-1155 log10 [log010] 2-2398 log1p 2-2399 log2 2-2400 logarithm base ten 2-2398 base two 2-2400 complex 2-2397 to 2-2398 natural 2-2397 of beta function (natural) 2-397 of gamma function (natural) 2-1672 of real numbers 2-3250 plotting 2-2403 logarithmic derivative gamma function 2-3118 logarithmically spaced vectors, creating 2-2409 logical 2-2401 logical array converting numeric array to 2-2401 detecting 2-2162 logical indexing 2-2401 logical operations AND, bit-wise 2-419 OR, bit-wise 2-426 XOR 2-4516 XOR, bit-wise 2-430 logical operators 2-56 2-63 logical OR bit-wise 2-426 logical tests 2-2123 all 2-151 any 2-212 See also detecting logical XOR 2-4516 bit-wise 2-430 loglog 2-2403 logm 2-2406 logspace 2-2409 lookfor 2-2410 lossy compression writing JPEG 2000 files with 2-2017 writing JPEG files with 2-2017 Lotus WK1 files loading 2-4474 writing 2-4477 lower 2-2412 lower triangular matrix 2-4030 lowercase to uppercase 2-4325 ls 2-2413 1scov 2-2415 lsgnonneg 2-2420 lsgr 2-2423 1t 2-2428 lu 2-2430 LU factorization 2-2430 storage requirements of (sparse) 2-2789 luinc 2-2438

Μ

.m files checking existence of 2-1307 M-file execution resuming after suspending 2-4221 suspending from GUI 2-4292 M-files clearing from workspace 2-790 deleting 2-1123 machine epsilon 2-4457 magic 2-2445 magic squares 2-2445 Map containers constructor 2-2450 2-3530 methods 2-2277 2-3323 2-4355 Map methods constructor 2-2157 2-2237 Margin annotation textbox property 2-206 text object 2-3944 Marker Line property 2-2323 lineseries property 2-2337 marker property 2-1274 Patch property 2-2941 quivergroup property 2-3197 scatter property 2-3440 stairseries property 2-3637 stem property 2-3671 Surface property 2-3832 surfaceplot property 2-3856 MarkerEdgeColor errorbar property 2-1274 Line property 2-2324 lineseries property 2-2338 Patch property 2-2941 quivergroup property 2-3197

scatter property 2-3440 stairseries property 2-3637 stem property 2-3672 Surface property 2-3833 surfaceplot property 2-3857 MarkerFaceColor errorbar property 2-1275 Line property 2-2324 lineseries property 2-2338 Patch property 2-2942 quivergroup property 2-3198 scatter property 2-3441 stairseries property 2-3638 stem property 2-3672 Surface property 2-3834 surfaceplot property 2-3857 MarkerSize errorbar property 2-1275 Line property 2-2325 lineseries property 2-2339 Patch property 2-2942 quivergroup property 2-3198 stairseries property 2-3638 stem property 2-3672 Surface property 2-3834 surfaceplot property 2-3858 mass matrix (ODE) 2-2831 initial slope 2-2832 to 2-2833 singular 2-2832 sparsity pattern 2-2832 specifying 2-2832 state dependence 2-2832 MAT-file 2-3404 converting sparse matrix after loading from 2-3562 MAT-files listing for folder 2-4447 mat2cell 2-2458 mat2str 2-2461 material 2-2463

MATLAB installation folder 2-2470 quitting 2-3177 startup 2-2469 version number, comparing 2-4370 version number, displaying 2-4364 matlab : function 2-2465 matlab (UNIX command) 2-2473 matlab (Windows command) 2-2485 MATLAB files listing names of in a folder 2-4447 matlab function for UNIX 2-2473 matlab function for Windows 2-2485 MATLAB startup file 2-3647 MATLAB[®] desktop moving figure windows in front of 2-3512 matlab.mat 2-3404matlabcolon function 2-2465 matlabrc 2-2469 matlabroot 2-2470 \$matlabroot 2-2470 matrices preallocation 2-4520 matrix 2-44 addressing selected rows and columns of 2-70 arrowhead 2-850 columns rearrange 2-1528 companion 2-858 condition number of 2-869 2-3238 condition number, improving 2-337 converting to vector 2-71 defective (defined) 2-1219 detecting sparse 2-2199 determinant of 2-1145 diagonal of 2-1151 Dulmage-Mendelsohn decomposition 2-1188 evaluating functions of 2-1625 exponential 2-1314

Hadamard 2-1806 2-3787 Hankel 2-1811 Hermitian Toeplitz 2-4020 Hessenberg form of 2-1855 Hilbert 2-1906 inverse 2-2110 inverse Hilbert 2-2113 inversion, accuracy of 2-869 involutary 2-2900 left division (arithmetic operator) 2-45 lower triangular 2-4030 magic squares 2-2445 2-3795 maximum size of 2-867 modal 2-1217 multiplication (defined) 2-45 Pascal 2-2900 2-3060 permutation 2-2430 poorly conditioned 2-1906 power (arithmetic operator) 2-46 pseudoinverse 2-3004 reading files into 2-1180 rearrange columns 2-1528 rows 2-1529 reduced row echelon form of 2-3399 replicating 2-3328 right division (arithmetic operator) 2-45 rotating 90\xfb 2-3388 rows rearrange 2-1529 Schur form of 2-3401 2-3448 singularity, test for 2-1145 sorting rows of 2-3552 sparse. See sparse matrix specialized 2-1644 square root of 2-3610 subspaces of 2-3787 test 2-1644 Toeplitz 2-4020 trace of 2-1151 2-4022

transpose (arithmetic operator) 2-46 transposing 2-67 unimodular 2-1677 unitary 2-3872 upper triangular 2-4051 Vandermonde 2-3055 Wilkinson 2-3568 2-4468 writing formatted data to 2-1596 writing to ASCII delimited file 2-1184 writing to spreadsheet 2-4477 See also array Matrix hgtransform property 2-1902 matrix functions evaluating 2-1625 matrix names, (M1 through M12) generating a sequence of 2-1288 matrix power. See matrix, exponential max 2-2491 max (timeseries) 2-2492 Max, Uicontrol property 2-4130 MaxHeadSize quivergroup property 2-3198 maximum matching 2-1188 MDL-files checking existence of 2-1307 mean 2-2497 mean (timeseries) 2-2498 median 2-2500 median (timeseries) 2-2501 median value of array elements 2-2500 memmapfile 2-2503 memory 2-2509 clearing 2-790 minimizing use of 2-2878 variables in 2-4461 menu (of user input choices) 2-2518 menu function 2-2518 MenuBar, Figure property 2-1428 Mersenne twister 2-3225 2-3229

mesh plot tetrahedron 2-3913 mesh size (BVP) 2-476 meshc 2-2520 meshgrid 2-2525 MeshStyle, Surface property 2-3834 MeshStyle, surfaceplot property 2-3858 meshz 2-2520 message error See error message 2-4421 warning See warning message 2-4421 meta.class 2-2527 meta.DynamicProperty 2-2532 meta.event 2-2536 meta.method 2-2538 meta.package class 2-2541 meta.property 2-2544 methods locating 2-4452 mex 2-2553 mex build script switches 2-2554 -arch 2-2555 -argcheck 2-2555 -c 2-2555 -compatibleArrayDims 2-2555 -cxx 2-2555 -Dname 2-2555 -Dname=value 2-2556 -f optionsfile 2-2556 -fortran 2-2556 -q 2-2556 -h[elp] 2-2556 -inline 2-2556 -Ipathname 2-2556 -largeArrayDims 2-2557 -Lfolder 2-2557 -lname 2-2557 -n 2-2557 name=value 2-2558

-0 2-2557 -outdir dirname 2-2557 -output resultname 2-2558 @rsp file 2-2554 -setup 2-2558 -Uname 2-2558 -v 2-2558 mex.CompilerConfiguration 2-2561 mex.CompilerConfigurationDetails 2-2561 MEX-files clearing from workspace 2-790 debugging on UNIX 2-1047 listing for folder 2-4447 mex.getCompilerConfigurations 2-2561 MException constructor 2-1251 2-2567 methods addCause 2-111 disp 2-1169 eq 2-1251 getReport 2-1741 isegual 2-2139 last 2-2240 ne 2-2689 rethrow 2-3348 throw 2-3980 throwAsCaller 2-3984 mexext 2-2573 mfilename 2-2574 mget function 2-2575 Microsoft Excel files loading 2-4495 min 2-2576 min (timeseries) 2-2577 Min, Uicontrol property 2-4131 MinColormap, Figure property 2-1429 MinorGridLineStyle, Axes property 2-316 minres 2-2581 minus (function equivalent for -) 2-49 mislocked 2-2586

mkdir 2-2587 mkdir (ftp) 2-2590 mkpp 2-2591 mldivide (function equivalent for) 2-49 mlint 2-2604 mlintrpt 2-2614 suppressing messages 2-2616 mlock 2-2617 mmfileinfo 2-2618 mod 2-2626 modal matrix 2-1217 mode 2-2628 mode objects pan, using 2-2883 rotate3d, using 2-3392 zoom, using 2-4525 models saving 2-3415 modification date of a file 2-1160 modified Bessel functions relationship to Airy functions 2-143 modulo arithmetic 2-2626 MonitorPositions Root property 2-3376 Moore-Penrose pseudoinverse 2-3004 more 2-2631 2-2656 move 2-2633 movefile 2-2635 movegui function 2-2638 movie 2-2641 movie2avi 2-2645 movies exporting in AVI format 2-282 mpower (function equivalent for $^{)}$ 2-50 mput function 2-2648 mrdivide (function equivalent for /) 2-49 msqbox 2-2649 mtimes 2-2652 mtimes (function equivalent for *) 2-49

mu-law encoded audio signals 2-2306 2-2656 multibandread 2-2657 multibandwrite 2-2662 multidimensional arrays concatenating 2-518 interpolation of 2-2096 number of dimensions of 2-2684 rearranging dimensions of 2-2117 2-2995 removing singleton dimensions of 2-3613 reshaping 2-3339 size of 2-3527 sorting elements of 2-3548 multiple least common 2-2253 multiplication array (arithmetic operator) 2-45 matrix (defined) 2-45 of polynomials 2-920 multistep ODE solver 2-2809 munlock 2-2668

Ν

Name, Figure property 2-1430 namelengthmax 2-2670 naming conventions functions 2-1615 NaN 2-2671 NaN (Not-a-Number) 2-2671 returned by rem 2-3322 nargchk 2-2673 nargoutchk 2-2677 native2unicode 2-2679 ndgrid 2-2682 ndims 2-2684 ne 2-2685 ne, MException method 2-2689 nearest neighbor interpolation 2-2079 2-2089 2-2093 2-2096 NET

summary of functions 2-2692 .NET summary of functions 2-2692 netcdf summary of capabilities 2-2710 2-2743 netcdf.abort revert recent netCDF file definitions 2-2713 netcdf.close close netCDF file 2-2715 netcdf.copyAtt copy attribute to new location 2-2716 netcdf.create create netCDF file 2-2718 netcdf.defDim create dimension in netCDF file 2-2720 netcdf.defVar define variable in netCDF dataset 2-2721 netcdf.delAtt delete netCDF attribute 2-2722 netcdf.endDef takes a netCDF file out of define mode 2-2724 netcdf.getAtt return data from netCDF attribute 2-2726 netcdf.getConstant get numeric value of netCDF constant 2-2728 netcdf.getConstantNames get list of netCDF constants 2-2729 netcdf.getVar return data from netCDF variable 2-2730 netcdf.ing return information about netCDF file 2-2733 netcdf.ingAtt return information about a netCDF attribute 2-2735 netcdf.ingAttID return identifier of netCDF attribute 2-2737 netcdf.ingAttName return name of netCDF attribute 2-2738 netcdf.ingDim

return information about netCDF dimension 2-2740 netcdf.ingDimID return dimension ID for netCDF file 2-2741 netcdf.ingLibVers return version of netCDF library 2-2742 netcdf.ingVarID return netCDF variable identifier 2-2745 netcdf.open open an existing netCDF file 2-2746 netcdf.putAtt write a netCDF attribute 2-2747 netcdf.putVar write data to netCDF variable 2-2749 netcdf.reDef put netCDF file into define mode 2-2751 netcdf.renameAtt netCDF function to change the name of an attribute 2-2752 netcdf.renameDim netCDF function to change the name of a dimension 2-2754 netcdf.renameVar change the name of a netCDF variable 2-2756 netcdf.setDefaultFormat change the default netCDF file format 2-2758 netcdf.setFill set netCDF fill behavior 2-2759 netcdf.sync synchronize netCDF dataset to disk 2-2760 newplot 2-2761 NextPlot Axes property 2-316 Figure property 2-1430 nextpow2 2-2765 nnz 2-2766 no derivative method 2-1542 nodesktop startup option 2-2477 nonzero entries

specifying maximum number of in sparse matrix 2-3559 nonzero entries (in sparse matrix) allocated storage for 2-2789 number of 2-2766 replacing with ones 2-3590 vector of 2-2768 nonzeros 2-2768 norm 2-2769 1-norm 2-2769 2-3238 2-norm (estimate of) 2-2771 F-norm 2-2769 infinity 2-2769 matrix 2-2769 pseudoinverse and 2-3004 2-3006 vector 2-2769 normal vectors, computing for volumes 2-2178 NormalMode Patch property 2-2943 Surface property 2-3835 surfaceplot property 2-3858 normest 2-2771 not 2-2772 not (function equivalent for ~) 2-60 notebook 2-2773 notify 2-2774 now 2-2775 nthroot 2-2776 null 2-2777 null space 2-2777 num2cell 2-2779 num2hex 2-2782 num2str 2-2783 number of array dimensions 2-2684 numbers imaginary 2-1950 NaN 2-2671 plus infinity 2-2037 prime 2-3071

real 2-3249 smallest positive 2-3252 NumberTitle, Figure property 2-1430 nume1 2-2787 numerical differentiation formula ODE solvers 2-2809 numerical evaluation double integral 2-1045 triple integral 2-4033 nzmax 2-2789

0

object determining class of 2-2123 object classes, list of predefined 2-2123 objects Java 2-2156 ODE file template 2-2812 **ODE** solver properties error tolerance 2-2819 event location 2-2826 Jacobian matrix 2-2827 mass matrix 2-2831 ode15s 2-2834 solver output 2-2821 step size 2-2824 **ODE** solvers backward differentiation formulas 2-2834 numerical differentiation formulas 2-2834 obtaining solutions at specific times 2-2797 variable order solver 2-2834 ode15i function 2-2790 odefile 2-2811 odeget 2-2817 odephas2 output function 2-2823 odephas3 output function 2-2823 odeplot output function 2-2823 odeprint output function 2-2823

odeset 2-2818 odextend 2-2836 off-screen figures, displaying 2-1503 OffCallback Uitoggletool property 2-4279 %#ok 2-2607 **OnCallback** Uitoggletool property 2-4279 one-step ODE solver 2-2808 ones 2-2841 online documentation, displaying 2-1850 online help 2-1846 openfig 2-2846 OpenGL 2-1437 autoselection criteria 2-1441 opening files in Windows applications 2-4469 openvar 2-2853 operating system MATLAB is running on 2-867 operating system command 2-3901 operating system command, issuing 2-68 operators arithmetic 2-44 logical 2-56 2-63 overloading arithmetic 2-50 overloading relational 2-54 relational 2-54 2-2401 symbols 2-1846 optimget 2-2857 optimization parameters structure 2-2857 to 2 - 2858optimizing file execution 2-3105 optimset 2-2858 or 2-2862 or (function equivalent for |) 2-60 ordeig 2-2864 orderfields 2-2867 ordering reverse Cuthill-McKee 2-3883 2-3893

ordgz 2-2870 ordschur 2-2872 orient 2-2874 orth 2-2876 orthographic projection, setting and guerving 2-499 otherwise 2-2877 Out of memory (error message) 2-2878 OuterPosition Axes property 2-316 Figure property 2-1431 output checking number of arguments 2-2677 controlling display format 2-1554 in Command Window 2-2631 number of arguments 2-2675 output points (ODE) increasing number of 2-2821 output properties (DDE) 2-1084 output properties (ODE) 2-2821 increasing number of output points 2-2821 overflow 2-2037 overloading arithmetic operators 2-50 relational operators 2-54 special characters 2-69

Ρ

P-files checking existence of 2-1307 pack 2-2878 padecoef 2-2880 pagesetupdlg 2-2881 paging of screen 2-1848 paging in the Command Window 2-2631 pan mode objects 2-2883 PaperOrientation, Figure property 2-1432 PaperPosition, Figure property 2-1432 PaperPositionMode, Figure property 2-1432 PaperSize, Figure property 2-1433 PaperType, Figure property 2-1433 PaperUnits, Figure property 2-1434 parametric curve, plotting 2-1340 Parent areaseries property 2-232 Axes property 2-318 barseries property 2-364 contour property 2-906 errorbar property 2-1275 Figure property 2-1435 hggroup property 2-1873 hgtransform property 2-1902 Image property 2-1971 Light property 2-2301 Line property 2-2325 lineseries property 2-2339 Patch property 2-2943 quivergroup property 2-3198 rectangle property 2-3275 Root property 2-3377 scatter property 2-3441 stairseries property 2-3638 stem property 2-3672 Surface property 2-3835 surfaceplot property 2-3859 Text property 2-3945 Uicontextmenu property 2-4106 Uicontrol property 2-4132 Uimenu property 2-4172 Uipushtool property 2-4209 Uitable property 2-4263 Uitoggletool property 2-4279 Uitoolbar property 2-4290 parentheses (special characters) 2-66 parfor 2-2893 parse method of inputParser object 2-2895 parseSoapResponse 2-2898

partial fraction expansion 2-3341 pascal 2-2900 Pascal matrix 2-2900 2-3060 patch 2-2901 Patch converting a surface to 2-3809 creating 2-2901 properties 2-2921 reducing number of faces 2-3280 reducing size of face 2-3516 path 2-2948 building from parts 2-1611 path2rc 2-2951 pathnames of functions or files 2-4452 pathsep 2-2952 pathtool 2-2953 pause 2-2955 pauses, removing 2-1040 pausing function execution 2-2955 pbaspect 2-2957 PBM parameters that can be set when writing 2-2018 PBM files writing 2-2013 pcg 2-2963 pchip 2-2967 pcode 2-2970 pcolor 2-2972 PCX files writing 2-2013 PDE. See Partial Differential Equations pdepe 2-2976 pdeval 2-2989 percent sign (special characters) 2-68 percent-brace (special characters) 2-68 perfect matching 2-1188 performance 2-374

period (.), to distinguish matrix and array operations 2-44 period (special characters) 2-67 perl 2-2992 perl function 2-2992 Perl scripts in MATLAB 2-2992 perms 2-2994 permutation matrix 2-2430 of array dimensions 2-2995 random 2-3223 permutations of n elements 2-2994 permute 2-2995 persistent 2-2996 persistent variable 2-2996 perspective projection, setting and guerving 2-499 PGM parameters that can be set when writing 2-2018 PGM files writing 2-2013 phase angle, complex 2-168 phase, complex correcting angles 2-4318 pie 2-3000 pie3 2-3002 pinv 2-3004 planerot 2-3007 platform MATLAB is running on 2-867 playshow function 2-3012 plot editing 2-3029 plot (timeseries) 2-3019 plot box aspect ratio of axes 2-2957 plot editing mode overview 2-3030 Plot Editor interface 2-3030 2-3113 plot, volumetric

generating grid arrays for 2-2525 slice plot 2-3536 PlotBoxAspectRatio, Axes property 2-318 PlotBoxAspectRatioMode, Axes property 2-318 plotedit 2-3029 plotting 3-D plot 2-3025 contours (a 2-1320 contours (ez function) 2-1320 ez-function mesh plot 2-1328 feather plots 2-1366 filled contours 2-1324 function plots 2-1562 functions with discontinuities 2-1348 histogram plots 2-1907 in polar coordinates 2-1343 isosurfaces 2-2181 loglog plot 2-2403 mathematical function 2-1336 mesh contour plot 2-1332 mesh plot 2-2520 parametric curve 2-1340 plot with two y-axes 2-3036 ribbon plot 2-3360 rose plot 2-3384 scatter plot 2-3032 scatter plot, 3-D 2-3426 semilogarithmic plot 2-3458 stem plot, 3-D 2-3658 surface plot 2-3803 surfaces 2-1346 velocity vectors 2-873 volumetric slice plot 2-3536 . See visualizing plus (function equivalent for +) 2-49 PNG writing options for 2-2019 alpha 2-2019 background color 2-2019 chromaticities 2-2020

gamma 2-2020 interlace type 2-2020 resolution 2-2021 significant bits 2-2020 transparency 2-2021 PNG files writing 2-2013 PNM files writing 2-2013 Pointer, Figure property 2-1435 PointerLocation, Root property 2-3377 PointerShapeCData, Figure property 2-1435 PointerShapeHotSpot, Figure property 2-1436 PointerWindow, Root property 2-3378 pol2cart 2-3041 polar 2-3043 polar coordinates 2-3041 computing the angle 2-168 converting from Cartesian 2-512 converting to cylindrical or Cartesian 2-3041 plotting in 2-1343 poles of transfer function 2-3341 poly 2-3045 polyarea 2-3048 polyder 2-3050 polyeig 2-3051 polyfit 2-3053 polygamma function 2-3118 polygon area of 2-3048 creating with patch 2-2901 detecting points inside 2-2046 polvint 2-3057 polynomial analytic integration 2-3057 characteristic 2-3045 to 2-3046 2-3382 coefficients (transfer function) 2-3341 curve fitting with 2-3053 derivative of 2-3050 division 2-1102

eigenvalue problem 2-3051 evaluation 2-3058 evaluation (matrix sense) 2-3060 make piecewise 2-2591 multiplication 2-920 polyval 2-3058 polyvalm 2-3060 poorly conditioned matrix 2-1906 poorly conditioned eigenvalues 2-337 pop-up menus 2-4110 defining choices 2-4135 Portable Anymap files writing 2-2013 Portable Bitmap (PBM) files writing 2-2013 Portable Graymap files writing 2-2013 Portable Network Graphics files writing 2-2013 Portable pixmap format writing 2-2013 Position annotation ellipse property 2-183 annotation line property 2-186 annotation rectangle property 2-190 arrow property 2-175 Axes property 2-319 doubletarrow property 2-180 Figure property 2-1436 Light property 2-2301 Text property 2-3945 textarrow property 2-195 textbox property 2-206 Uicontextmenu property 2-4106 Uicontrol property 2-4132 Uimenu property 2-4173 Uitable property 2-4263 position of camera dollying 2-485

position of camera, setting and querying 2-497 Position, rectangle property 2-3275 PostScript default printer 2-3079 levels 1 and 2 2-3079 printing interpolated shading 2-3089 pow2 2-3062 power 2-3063 matrix. See matrix exponential of real numbers 2-3253 of two, next 2-2765 power (function equivalent for $.^{)}$ 2-50 PPM parameters that can be set when writing 2-2018 PPM files writing 2-2013 ppval 2-3064 preallocation matrix 2-4520 precision 2-1554 prefdir 2-3066 preferences 2-3070 opening the dialog box 2-3070 present working directory 2-3136 prime factors 2-1360 dependence of Fourier transform on 2-1382 2-1384 to 2-1385 prime numbers 2-3071 primes 2-3071 printdlg 2-3093 printdlg function 2-3093 printer default for linux and unix 2-3079 printer drivers GhostScript drivers 2-3074 interploated shading 2-3089 MATLAB printer drivers 2-3074 printing GUIs 2-3088

interpolated shading 2-3089 on MS-Windows 2-3087 with a variable file name 2-3090 with nodisplay 2-3082 with noFigureWindows 2-3082 with non-normal EraseMode 2-2321 2-2933 2-3272 2-3828 2-3933 printing figures preview 2-3094 printing tips 2-3087 printing, suppressing 2-67 printpreview 2-3094 prod 2-3103 product cumulative 2-979 Kronecker tensor 2-2238 of array elements 2-3103 of vectors (cross) 2-966 scalar (dot) 2-966 profile 2-3105 profsave 2-3112 projection type, setting and querying 2-499 ProjectionType, Axes property 2-319 prompting users for input 2-2048 prompting users to choose an item 2-2518 propedit 2-3113 to 2-3114 proppanel 2-3117 pseudoinverse 2-3004 psi 2-3118 push buttons 2-4111 pwd 2-3136

Q

qmr 2-3137 QR decomposition deleting column from 2-3145 qrdelete 2-3145 qrinsert 2-3147 qrupdate 2-3149 quad 2-3152 quadgk 2-3161 quadl 2-3167 quadrature 2-3152 2-3161 quadv 2-3170 quantization performed by rgb2ind 2-3356 questdlg 2-3173 questdlg function 2-3173 quit 2-3177 quitting MATLAB 2-3177 quiver 2-3180 quiver3 2-3183 qz 2-3208 QZ factorization 2-3052 2-3208

R

radio buttons 2-4111 rand, RandStream method 2-3212 randi, RandStream method 2-3217 randn, RandStream method 2-3222 random permutation 2-3223 sparse matrix 2-3596 to 2-3597 symmetric sparse matrix 2-3598 random number generators 2-2371 2-3212 2-3217 2-3222 2-3225 2-3229 randperm 2-3223 randStream constructor 2-3229 RandStream 2-3225 2-3229 constructor 2-3225 methods create 2-956 get 2-1704 getDefaultStream 2-1721 list 2-2371 rand 2-3212 randi 2-3217

randn 2-3222 setDefaultStream 2-3490 range space 2-2876 rank 2-3231 rank of a matrix 2-3231 **RAS** files parameters that can be set when writing 2-2022 writing 2-2014 RAS image format specifying color order 2-2022 writing alpha data 2-2022 Raster image files writing 2-2014 rational fraction approximation 2-3232 rbbox 2-3236 2-3287 rcond 2-3238 rdivide (function equivalent for ./) 2-49 readasync 2-3243 reading data from files 2-3954 formatted data from file 2-1596 readme files, displaying 2-2130 2-4451 real 2-3249 real numbers 2-3249 reallog 2-3250 realmax 2-3251 realmin 2-3252 realpow 2-3253 realsqrt 2-3254 rearrange array flip along dimension 2-1527 reverse along dimension 2-1527 rearrange matrix flip left-right 2-1528 flip up-down 2-1529 reverse column order 2-1528 reverse row order 2-1529 RearrangeableColumn Uitable property 2-4264

rearranging arrays converting to vector 2-71 removing first n singleton dimensions 2-3513 removing singleton dimensions 2-3613 reshaping 2-3339 shifting dimensions 2-3513 swapping dimensions 2-2117 2-2995 rearranging matrices converting to vector 2-71 rotating 90\xfb 2-3388 transposing 2-67 record 2-3255 rectangle properties 2-3264 rectangle function 2-3259 rectint 2-3277 RecursionLimit Root property 2-3378 recycle 2-3278 reduced row echelon form 2-3399 reducepatch 2-3280 reducevolume 2-3284 reference page accessing from doc 2-1191 refresh 2-3287 regexprep 2-3307 regexptranslate 2-3311 regression linear 2-3053 regularly spaced vectors, creating 2-70 2-2370 rehash 2-3316 relational operators 2-54 2-2401 relational operators for handle objects 2-3320 relative accuracy BVP 2-472 DDE 2-1083 norm of DDE solution 2-1083 norm of ODE solution 2-2820 ODE 2-2820 rem 2-3322

removets 2-3325 rename function 2-3327 renaming using copyfile 2-933 renderer OpenGL 2-1437 painters 2-1437 zbuffer 2-1437 Renderer, Figure property 2-1437 RendererMode, Figure property 2-1441 repeatedly executing statements 2-1552 2-4455 repeatedly executing statements in parallel 2-2894 replicating a matrix 2-3328 repmat 2-3328 resample (timeseries) 2-3330 resample (tscollection) 2-3333 reset 2-3336 reshape 2-3339 residue 2-3341 residues of transfer function 2-3341 Resize, Figure property 2-1442 ResizeFcn, Figure property 2-1442 restoredefaultpath 2-3345 rethrow 2-3346 rethrow, MException method 2-3348 return 2-3352 reverse array along dimension 2-1527 array dimension 2-1527 matrix column order 2-1528 matrix row order 2-1529 reverse Cuthill-McKee ordering 2-3883 2-3893 **RGB** images converting to indexed 2-3355 RGB, converting to HSV 2-3354 rgb2hsv 2-3354 rgb2ind 2-3355 rgbplot 2-3358 ribbon 2-3360

right-click and context menus 2-4097 rmappdata function 2-3363 rmdir 2-3364 rmdir (ftp) function 2-3367 rmfield 2-3368 rmpath 2-3369 rmpref function 2-3370 RMS. See root-mean-square rolling camera 2-501 root folder 2-2470 Root graphics object 2-3371 root object 2-3371 root, see rootobject 2-3371 root-mean-square of vector 2-2769 roots 2-3382 roots of a polynomial 2-3045 to 2-3046 2-3382 rose 2-3384 Rosenbrock banana function 2-1540 ODE solver 2-2809 rosser 2-3387 rot90 2-3388 rotate 2-3389 rotate3d 2-3392 rotate3d mode objects 2-3392 rotating camera 2-493 rotating camera target 2-495 Rotation, Text property 2-3946 rotations Jacobi 2-3598 round 2-3398 to nearest integer 2-3398 towards infinity 2-722 towards minus infinity 2-1531 towards zero 2-1526 roundoff error characteristic polynomial and 2-3046 effect on eigenvalues 2-337 evaluating matrix functions 2-1628

in inverse Hilbert matrix 2-2113
 partial fraction expansion and 2-3342
 polynomial roots and 2-3382
 sparse matrix conversion and 2-3563
RowName
 Uitable property 2-4264
RowStriping
 Uitable property 2-4265
rref 2-3399
rrefmovie 2-3399
rsf2csf 2-3401
rubberband box 2-3236
run 2-3403
Runge-Kutta ODE solvers 2-2808
running average 2-1490

S

save 2-3404 2-3411 serial port I/O 2-3413 saveas 2-3415 savepath 2-3421 saving ASCII data 2-3404 session to a file 2-1155 workspace variables 2-3404 scalar product (of vectors) 2-966 scaled complementary error function (defined) 2-1252 scatter 2-3423 scatter3 2-3426 scattered data, aligning multi-dimensional 2-2682 scattergroup properties 2-3429 Schmidt semi-normalized Legendre functions 2-2272 schur 2-3448 Schur decomposition 2-3448 Schur form of matrix 2-3401 2-3448

screen, paging 2-1848 ScreenDepth, Root property 2-3378 ScreenPixelsPerInch, Root property 2-3379 ScreenSize, Root property 2-3379 script 2-3451 declaration 2-1615 scrolling screen 2-1848 search path adding folders to 2-126 **MATLAB 2-2948** modifying 2-2953 removing folders from 2-3369 toolbox folder 2-4021 user folder 2-4331 viewing 2-2953 search, string 2-1511 sec 2-3452 secant 2-3452 hyperbolic 2-3455 inverse 2-244 inverse hyperbolic 2-247 secd 2-3454 sech 2-3455 Selected areaseries property 2-232 Axes property 2-320 barseries property 2-364 contour property 2-906 errorbar property 2-1275 Figure property 2-1444 hggroup property 2-1873 hgtransform property 2-1902 Image property 2-1972 Light property 2-2302 Line property 2-2325 lineseries property 2-2339 Patch property 2-2943 quivergroup property 2-3199 rectangle property 2-3275 Root property 2-3379

scatter property 2-3441 stairseries property 2-3638 stem property 2-3673 Surface property 2-3835 surfaceplot property 2-3859 Text property 2-3946 Uicontrol property 2-4133 Uitable property 2-4265 selecting areas 2-3236 SelectionHighlight areaseries property 2-232 Axes property 2-320 barseries property 2-364 contour property 2-907 errorbar property 2-1276 Figure property 2-1444 hggroup property 2-1873 hgtransform property 2-1902 Image property 2-1972 Light property 2-2302 Line property 2-2325 lineseries property 2-2339 Patch property 2-2943 quivergroup property 2-3199 rectangle property 2-3275 scatter property 2-3441 stairseries property 2-3639 stem property 2-3673 Surface property 2-3835 surfaceplot property 2-3859 Text property 2-3946 Uicontrol property 2-4133 Uitable property 2-4265 SelectionType, Figure property 2-1444 selectmoveresize 2-3457 semicolon (special characters) 2-67 sendmail 2-3461 Separator Uipushtool property 2-4210 Uitoggletool property 2-4279

Separator, Uimenu property 2-4173 sequence of matrix names (M1 through M12) generating 2-1288 serial 2-3463 serialbreak 2-3466 server (FTP) connecting to 2-1608 server variable 2-1374 session saving 2-1155 set 2-3467 2-3475 serial port I/O 2-3480 timer object 2-3482 set (timeseries) 2-3485set (tscollection) 2-3486 set hgsetget class method 2-3476 set operations difference 2-3491 exclusive or 2-3509 intersection 2-2103 membership 2-2164 union 2-4296 unique 2-4298 setabstime (timeseries) 2-3487 setabstime (tscollection) 2-3488 setappdata 2-3489 setDefaultStream, RandStream method 2-3490 setdiff 2-3491 setdisp hgsetget class method 2-3493 setenv 2-3494 setinterpmethod 2-3498 setpixelposition 2-3500 setpref function 2-3503 setstr 2-3504 settimeseriesnames 2-3508 setxor 2-3509 shading 2-3510 shading colors in surface plots 2-3510 shared libraries MATLAB functions

calllib 2-481 libfunctions 2-2281 libfunctionsview 2-2282 libisloaded 2-2283 libpointer 2-2285 libstruct 2-2287 loadlibrary 2-2388 unloadlibrary 2-4304 shell script 2-3901 2-4301 shiftdim 2-3513 shifting array circular 2-774 ShowArrowHead quivergroup property 2-3199 ShowBaseLine barseries property 2-364 ShowHiddenHandles, Root property 2-3380 showplottool 2-3514 ShowText contour property 2-907 shrinkfaces 2-3516 shutdown 2-3177 sign 2-3520 signum function 2-3520 simplex search 2-1542 Simpson's rule, adaptive recursive 2-3154 Simulink version number, comparing 2-4370 version number, displaying 2-4364 sine hyperbolic 2-3525 inverse hyperbolic 2-253 single 2-3524 single quote (special characters) 2-67 singular value decomposition 2-3231 2-3872 largest 2-2769 rank and 2-3231 sinh 2-3525 size

Index

array dimesions 2-3527 serial port I/O 2-3532 size (timeseries) 2-3533 size (tscollection) 2-3535 size of array dimensions 2-3527 size of fonts, see also FontSize property 2-3949 size vector 2-3339 SizeData scatter property 2-3442 SizeDataSource scatter property 2-3442 slice 2-3536 slice planes, contouring 2-915 sliders 2-4111 SliderStep, Uicontrol property 2-4133 smallest array elements 2-2576 smooth3 2-3542 smoothing 3-D data 2-3542 soccer ball (example) 2-3893 solution statistics (BVP) 2-477 sort 2-3548 sorting array elements 2-3548 complex conjugate pairs 2-954 matrix rows 2-3552 sortrows 2-3552sound 2-3555 2-3557 converting vector into 2-3555 2-3557 files reading 2-279 2-4432 writing 2-281 2-4438 playing 2-4430 recording 2-4436 resampling 2-4430 sampling 2-4436 source control on UNIX platforms checking out files function 2-755 source control systems checking in files 2-752

undo checkout 2-4294 spalloc 2-3558 sparse 2-3559 sparse matrix allocating space for 2-3558 applying function only to nonzero elements of 2-3576 density of 2-2766 detecting 2-2199 diagonal 2-3564 finding indices of nonzero elements of 2-1497 identity 2-3575 number of nonzero elements in 2-2766 permuting columns of 2-850 random 2-3596 to 2-3597 random symmetric 2-3598 replacing nonzero elements of with ones 2-3590 results of mixed operations on 2-3560 specifying maximum number of nonzero elements 2-3559 vector of nonzero elements 2-2768 visualizing sparsity pattern of 2-3607 sparse storage criterion for using 2-1610 spaugment 2-3561 spconvert 2-3562 spdiags 2-3564 special characters descriptions 2-1846 overloading 2-69 specular 2-3574 SpecularColorReflectance Patch property 2-2944 Surface property 2-3835 surfaceplot property 2-3859 SpecularExponent Patch property 2-2944 Surface property 2-3836 surfaceplot property 2-3860

SpecularStrength Patch property 2-2944 Surface property 2-3836 surfaceplot property 2-3860 speye 2-3575 spfun 2-3576 sph2cart 2-3578 sphere 2-3579 sphereical coordinates defining a Light position in 2-2304 spherical coordinates 2-3578 spinmap 2-3582 spline 2-3583 spline interpolation (cubic) one-dimensional 2-2080 2-2090 2-2093 2 - 2096Spline Toolbox 2-2085 spones 2-3590 spparms 2-3591 sprand 2-3596 sprandn 2-3597 sprandsym 2-3598 sprank 2-3599 spreadsheets loading WK1 files 2-4474 loading XLS files 2-4495 reading into a matrix 2-1180 writing from matrix 2-4477 writing matrices into 2-1184 sqrt 2-3609 sgrtm 2-3610 square root of a matrix 2-3610 of array elements 2-3609 of real numbers 2-3254 squeeze 2-3613 stack, displaying 2-1051 standard deviation 2-3648 start timer object 2-3644

startat timer object 2-3645 startup 2-3647 folder and path 2-4331 startup file 2-3647 startup files 2-2469 State Uitoggletool property 2-4280 static text 2-4111 std 2-3648 std (timeseries) 2-3650 stem 2-3652 stem3 2-3658 step size (DDE) initial step size 2-1087 upper bound 2-1087 step size (ODE) 2-1086 2-2824 initial step size 2-2825 upper bound 2-2825 stop timer object 2-3679 stopasync 2-3680 stopwatch timer 2-3987 storage allocated for nonzero entries (sparse) 2-2789 sparse 2-3559 storage allocation 2-4520 str2cell 2-745 str2double 2-3681 str2func 2-3682 str2mat 2-3686 str2num 2-3687 strcat 2-3691 stream lines computing 2-D 2-3697 computing 3-D 2-3699 drawing 2-3701 stream2 2-3697 stream3 2-3699 stretch-to-fill 2-289

strfind 2-3730 string comparing one to another 2-3693 2-3736 converting from vector to 2-751 converting matrix into 2-2461 2-2783 converting to lowercase 2-2412 converting to numeric array 2-3687 converting to uppercase 2-4325 dictionary sort of 2-3552 finding first token in 2-3751 searching and replacing 2-3748 searching for 2-1511 String Text property 2-3946 textarrow property 2-195 textbox property 2-207 Uicontrol property 2-4134 string matrix to cell array conversion 2-745 strings 2-3732 strjust 2-3734 strmatch 2-3735 strread 2-3739 strrep 2-3748 strtok 2-3751 strtrim 2-3755 struct 2-3756 struct2cell 2-3761 structfun 2-3762 structure array getting contents of field of 2-1724 remove field from 2-3368 setting contents of a field of 2-3496 structure arrays field names of 2-1403 structures dynamic fields 2-67 strvcat 2-3765 Style Light property 2-2302 Uicontrol property 2-4137

sub2ind 2-3767 subfunction 2-1615 subplot 2-3770 subplots assymptrical 2-3775 suppressing ticks in 2-3778 subscripts in axis title 2-4017 in text strings 2-3950 subspace 2-3787subsref (function equivalent for A(i,j,k...)) 2-68 subtraction (arithmetic operator) 2-44 subvolume 2-3792 sum 2-3795 cumulative 2-981 of array elements 2-3795 sum (timeseries) 2-3798 superscripts in axis title 2-4017 in text strings 2-3950 support 2-3802 surf2patch 2-3809 surface 2-3811 Surface and contour plotter 2-1353 converting to a patch 2-3809 creating 2-3811 defining default properties 2-3262 2-3815 plotting mathematical functions 2-1346 properties 2-3816 2-3839 surface normals, computing for volumes 2-2178 surfl 2-3866 surfnorm 2-3870svd 2-3872 svds 2-3875 swapbytes 2-3878 switch 2-3880 symamd 2-3882 symbfact 2-3886

symbols operators 2-1846 symbols in text 2-196 2-207 2-3947 symmlq 2-3888 symrcm 2-3893 synchronize 2-3896 syntax, command 2-3898 syntax, function 2-3898 syntaxes function, defining 2-1615 system 2-3901 UNC pathname error 2-3902 system folder temporary 2-3911

T

table lookup. See interpolation Tag areaseries property 2-232 Axes property 2-320 barseries property 2-365 contour property 2-907 errorbar property 2-1276 Figure property 2-1445 hggroup property 2-1873 hgtransform property 2-1903 Image property 2-1972 Light property 2-2302 Line property 2-2326 lineseries property 2-2340 Patch property 2-2944 quivergroup property 2-3199 rectangle property 2-3275 Root property 2-3380 scatter property 2-3443 stairseries property 2-3639 stem property 2-3673 Surface property 2-3836 surfaceplot property 2-3860

Text property 2-3951 Uicontextmenu property 2-4107 Uicontrol property 2-4137 Uimenu property 2-4173 Uipushtool property 2-4210 Uitable property 2-4265 Uitoggletool property 2-4280 Uitoolbar property 2-4290 Tagged Image File Format (TIFF) writing 2-2014 tan 2-3904 tand 2-3906 tangent 2-3904 four-quadrant, inverse 2-261 hyperbolic 2-3907 inverse 2-259 inverse hyperbolic 2-264 tanh 2-3907 tar 2-3909 target, of camera 2-502 tempdir 2-3911 tempname 2-3912 temporary files 2-3912 system folder 2-3911 tensor, Kronecker product 2-2238 terminating MATLAB 2-3177 test matrices 2-1644 test, logical. See logical tests and detecting tetrahedron mesh plot 2-3913 tetramesh 2-3913 TeX commands in text 2-196 2-207 2-3947 text 2-3918 editing 2-3029 subscripts 2-3950 superscripts 2-3950 Text creating 2-3918 defining default properties 2-3921

fixed-width font 2-3935 properties 2-3923 TextBackgroundColor textarrow property 2-198 TextColor textarrow property 2-198 TextEdgeColor textarrow property 2-198 TextLineWidth textarrow property 2-198 TextList contour property 2-908 TextListMode contour property 2-908 TextMargin textarrow property 2-198 textread 2-3954 TextRotation, textarrow property 2-199 textscan 2-3960 TextStep contour property 2-909 TextStepMode contour property 2-909 textwrap 2-3974 tfqmr 2-3977 throw, MException method 2-3980 throwAsCaller, MException method 2-3984 TickDir, Axes property 2-321 TickDirMode, Axes property 2-321 TickLength, Axes property 2-321 TIFF compression 2-2023 encoding 2-2018 ImageDescription field 2-2023 maxvalue 2-2018 parameters that can be set when writing 2-2022 resolution 2-2023 writemode 2-2023 writing 2-2014

TIFF image format specifying color space 2-2022 tiling (copies of a matrix) 2-3328 time CPU 2-955 elapsed (stopwatch timer) 2-3987 required to execute commands 2-1284 time and date functions 2-1245 timer properties 2-4002 timer object 2-4002 timerfind timer object 2-4009 timerfindall timer object 2-4011 times (function equivalent for .*) 2-49 timeseries 2-4013 timestamp 2-1160 title 2-4016 with superscript 2-4017 Title, Axes property 2-322 todatenum 2-4019 toeplitz 2-4020 Toeplitz matrix 2-4020 toggle buttons 2-4111 token 2-3751 See also string Toolbar Figure property 2-1446 Toolbox Spline 2-2085 toolbox folder, path 2-4021 toolboxdir 2-4021 TooltipString Uicontrol property 2-4137 Uipushtool property 2-4210 Uitable property 2-4266 Uitoggletool property 2-4280 trace 2-4022 trace of a matrix 2-1151 2-4022

trailing blanks removing 2-1094 transform hgtransform function 2-1881 transform, Fourier discrete, n-dimensional 2-1385 discrete, one-dimensional 2-1379 discrete, two-dimensional 2-1384 inverse, n-dimensional 2-1940 inverse, one-dimensional 2-1936 inverse, two-dimensional 2-1938 shifting the zero-frequency component of 2-1388 transformation See also conversion 2-535 transformations elementary Hermite 2-1677 transmitting file to FTP server 2-2648 transpose array (arithmetic operator) 2-46 matrix (arithmetic operator) 2-46 transpose (function equivalent for . g) 2-50transpose (timeseries) 2-4023 trapz 2-4025 treelayout 2-4027 treeplot 2-4028 triangulation 2-D plot 2-4035 tril 2-4030 trimesh 2-4031 triple integral numerical evaluation 2-4033 tripleguad 2-4033 triplot 2-4035 trisurf 2-4049 triu 2-4051 true 2-4052 truth tables (for logical operations) 2-56 try 2-4053 tscollection 2-4057

tsdata.event 2-4060 tsearchn 2-4062 tsprops 2-4063 tstool 2-4068 type 2-4069 Туре areaseries property 2-233 Axes property 2-322 barseries property 2-365 contour property 2-909 errorbar property 2-1276 Figure property 2-1446 hggroup property 2-1874 hgtransform property 2-1903 Image property 2-1973 Light property 2-2302 Line property 2-2326 lineseries property 2-2340 Patch property 2-2945 quivergroup property 2-3200 rectangle property 2-3276 Root property 2-3380 scatter property 2-3443 stairseries property 2-3640 stem property 2-3674 Surface property 2-3836 surfaceplot property 2-3861 Text property 2-3951 Uicontextmenu property 2-4107 Uicontrol property 2-4138 Uimenu property 2-4173 Uipushtool property 2-4211 Uitable property 2-4266 Uitoggletool property 2-4281 Uitoolbar property 2-4291 typecast 2-4070

U

UData

errorbar property 2-1277 quivergroup property 2-3201 UDataSource errorbar property 2-1277 quivergroup property 2-3201 Uibuttongroup defining default properties 2-4079 uibuttongroup function 2-4074 **Uibuttongroup Properties 2-4079** uicontextmenu 2-4097 **UiContextMenu** Uicontrol property 2-4138 Uipushtool property 2-4211 Uitoggletool property 2-4281 Uitoolbar property 2-4291 UIContextMenu areaseries property 2-233 Axes property 2-323 barseries property 2-365 contour property 2-910 errorbar property 2-1277 Figure property 2-1447 hggroup property 2-1874 hgtransform property 2-1903 Image property 2-1973 Light property 2-2303 Line property 2-2326 lineseries property 2-2340 Patch property 2-2945 quivergroup property 2-3200 rectangle property 2-3276 scatter property 2-3443 stairseries property 2-3640 stem property 2-3674 Surface property 2-3837 surfaceplot property 2-3861 Text property 2-3951 Uitable property 2-4266 **Uicontextmenu Properties 2-4100** uicontrol 2-4108

Uicontrol defining default properties 2-4114 fixed-width font 2-4124 types of 2-4108 **Uicontrol Properties 2-4114** uicontrols printing 2-3088 uigetdir 2-4141 uigetfile 2-4145 uigetpref function 2-4156 uiimport 2-4160 uimenu 2-4161 Uimenu creating 2-4161 defining default properties 2-4163 Properties 2-4163 **Uimenu Properties 2-4163** uint16 2-4175 uint32 2-4175 uint64 2-4175 uint8 2-2075 2-4175 uiopen 2-4177 Uipanel defining default properties 2-4182 uipanel function 2-4179 **Uipanel Properties 2-4182** uipushtool 2-4199 Uipushtool defining default properties 2-4202 **Uipushtool Properties 2-4202** uiputfile 2-4212 uiresume 2-4221 uisave 2-4223 uisetcolor function 2-4226 uisetfont 2-4227uisetpref function 2-4229 uistack 2-4230 Uitable defining default properties 2-4239 fixed-width font 2-4258

uitable function 2-4231**Uitable Properties 2-4239** uitoggletool 2-4268 Uitoggletool defining default properties 2-4271 **Uitoggletool Properties 2-4271** uitoolbar 2-4282 Uitoolbar defining default properties 2-4284 **Uitoolbar Properties 2-4284** uiwait 2-4292 uminus (function equivalent for unary \xd0) 2-49 UNC pathname error and dos 2-1197 UNC pathname error and system 2-3902 unconstrained minimization 2-1538 undefined numerical results 2-2671 undocheckout 2-4294unicode2native 2-4295unimodular matrix 2-1677 union 2-4296 unique 2-4298 Units annotation ellipse property 2-183 annotation rectangle property 2-190 arrow property 2-175 Axes property 2-323 doublearrow property 2-180 Figure property 2-1447 line property 2-186 Root property 2-3380 Text property 2-3951 textarrow property 2-199 textbox property 2-209 Uicontrol property 2-4138 Uitable property 2-4266 unix 2-4301 unloadlibrary 2-4304 unlocking functions 2-2668 unmkpp 2-4309

untar 2-4316 unwrap 2-4318 unzip 2-4323 up vector, of camera 2-504 updating figure during file execution 2-1202 uplus (function equivalent for unary +) 2-49 upper 2-4325 upper triangular matrix 2-4051 uppercase to lowercase 2-2412 url opening in Web browser 2-4440 usejava 2-4329 user input from a button menu 2-2518 UserData areaseries property 2-233 Axes property 2-324 barseries property 2-366 contour property 2-910 errorbar property 2-1278 Figure property 2-1448 hggroup property 2-1874 hgtransform property 2-1904 Image property 2-1973 Light property 2-2303 Line property 2-2326 lineseries property 2-2341 Patch property 2-2945 quivergroup property 2-3200 rectangle property 2-3276 Root property 2-3381 scatter property 2-3444 stairseries property 2-3640 stem property 2-3674 Surface property 2-3837 surfaceplot property 2-3861 Text property 2-3952 Uicontextmenu property 2-4107 Uicontrol property 2-4139 Uimenu property 2-4173

Uipushtool property 2-4211 Uitable property 2-4267 Uitoggletool property 2-4281 Uitoolbar property 2-4291 userpath 2-4331

V

validateattributes 2-4340 validatestring 2-4349 Value, Uicontrol property 2-4139 vander 2-4356 Vandermonde matrix 2-3055 var 2-4357 var (timeseries) 2-4358 varargin 2-4360 varargout 2-4362 variable numbers of arguments 2-4362 variable-order solver (ODE) 2-2834 variables checking existence of 2-1307 clearing from workspace 2-790 global 2-1763 in workspace 2-4479 keeping some when clearing 2-796 linking to graphs with linkdata 2-2355 listing 2-4461 local 2-1615 2-1763 name of passed 2-2053 opening 2-2853 persistent 2-2996 saving 2-3404 sizes of 2-4461 VData quivergroup property 2-3202 VDataSource quivergroup property 2-3202 vector dot product 2-1198 frequency 2-2409

product (cross) 2-966 vector field, plotting 2-873 vectorize 2-4363 vectorizing ODE function (BVP) 2-474 vectors, creating logarithmically spaced 2-2409 regularly spaced 2-70 2-2370 velocity vectors, plotting 2-873 ver 2-4364 verctrl function (Windows) 2-4366 verLessThan 2-4370 version 2-4372version numbers comparing 2-4370 displaying 2-4364 vertcat 2-4374 vertcat (function equivalent for [2-68 vertcat (timeseries) 2-4376 vertcat (tscollection) 2-4377 VertexNormals Patch property 2-2945 Surface property 2-3837 surfaceplot property 2-3861 VerticalAlignment, Text property 2-3952 VerticalAlignment, textbox property 2-199 2 - 209Vertices, Patch property 2-2946 video saving in AVI format 2-282 view 2-4381 azimuth of viewpoint 2-4381 coordinate system defining 2-4382 elevation of viewpoint 2-4381 view angle, of camera 2-506 View, Axes property (obsolete) 2-324 viewing a group of object 2-491 a specific object in a scene 2-491 viewmtx 2-4384 Visible

areaseries property 2-234 Axes property 2-324 barseries property 2-366 contour property 2-910 errorbar property 2-1278 Figure property 2-1448 hggroup property 2-1875 hgtransform property 2-1904 Image property 2-1973 Light property 2-2303 Line property 2-2326 lineseries property 2-2341 Patch property 2-2946 quivergroup property 2-3201 rectangle property 2-3276 Root property 2-3381 scatter property 2-3444 stairseries property 2-3640 stem property 2-3674 Surface property 2-3837 surfaceplot property 2-3862 Text property 2-3953 Uicontextmenu property 2-4107 Uicontrol property 2-4140 Uimenu property 2-4174 Uipushtool property 2-4211 Uitable property 2-4267 Uitoggletool property 2-4281 Uitoolbar property 2-4291 visualizing cell array structure 2-743 sparse matrices 2-3607 volumes calculating isosurface data 2-2181 computing 2-D stream lines 2-3697 computing 3-D stream lines 2-3699 computing isosurface normals 2-2178 contouring slice planes 2-915 drawing stream lines 2-3701 end caps 2-2171

reducing face size in isosurfaces 2-3516 reducing number of elements in 2-3284 voronoi 2-4397 Voronoi diagrams multidimensional vizualization 2-4404 two-dimensional vizualization 2-4397 voronoin 2-4404

W

wait timer object 2-4408 waitbar 2-4409 waitfor 2-4413 waitforbuttonpress 2-4417 warndlg 2-4418 warning 2-4421 warning message (enabling, suppressing, and displaying) 2-4421 waterfall 2-4425 .wav files reading 2-4432 writing 2-4438 waverecord 2-4436 wavfinfo 2-4429 wavplay 2-4430 wavread 2-4429 2-4432 wavrecord 2-4436 wavwrite 2-4438 WData quivergroup property 2-3203 WDataSource quivergroup property 2-3203 web 2-4440 Web browser displaying help in 2-1850 pointing to file or url 2-4440 weekday 2-4445well conditioned 2-3238 what 2-4447

whatsnew 2-4451 which 2-4452 while 2-4455 white space characters, ASCII 2-2198 2-3751 whitebg 2-4459 who, whos who 2-4461 wilkinson 2-4468 Wilkinson matrix 2-3568 2-4468 WindowButtonDownFcn, Figure property 2-1448 WindowButtonMotionFcn, Figure property 2-1449 WindowButtonUpFcn, Figure property 2-1450 WindowKeyPressFcn, Figure property 2-1450 WindowKeyReleaseFcn , Figure property 2-1452 Windows Paintbrush files writing 2-2013 WindowScrollWheelFcn, Figure property 2-1452 WindowStyle, Figure property 2-1455 winopen 2-4469 winqueryreg 2-4471 WK1 files loading 2-4474 writing from matrix 2-4477 wk1finfo 2-4473 wk1read 2-4474 wk1write 2-4477 workspace 2-4479 changing context while debugging 2-1044 2 - 1069clearing items from 2-790 consolidating memory 2-2878 predefining variables 2-3647 saving 2-3404 variables in 2-4461 viewing contents of 2-4479 workspace variables reading from disk 2-2379 WVisual, Figure property 2-1457 WVisualMode, Figure property 2-1459

X

Х annotation arrow property 2-176 2-180 annotation line property 2-187 textarrow property 2-200 X Windows Dump files writing 2-2014 x-axis limits, setting and querying 2-4490 XAxisLocation, Axes property 2-324 XColor, Axes property 2-325 XData areaseries property 2-234 barseries property 2-366 contour property 2-910 errorbar property 2-1278 Image property 2-1974 Line property 2-2327 lineseries property 2-2341 Patch property 2-2946 quivergroup property 2-3204 scatter property 2-3444 stairseries property 2-3640 stem property 2-3675 Surface property 2-3837 surfaceplot property 2-3862 XDataMode areaseries property 2-234 barseries property 2-366 contour property 2-911 errorbar property 2-1278 lineseries property 2-2341 quivergroup property 2-3204 stairseries property 2-3641 stem property 2-3675 surfaceplot property 2-3862 **XDataSource** areaseries property 2-235 barseries property 2-367 contour property 2-911 errorbar property 2-1279

lineseries property 2-2342 quivergroup property 2-3204 scatter property 2-3444 stairseries property 2-3641 stem property 2-3675 surfaceplot property 2-3862 XDir, Axes property 2-325 XDisplay, Figure property 2-1460 XGrid, Axes property 2-326 xlabel 2-4488 XLabel, Axes property 2-326 xlim 2-4490 XLim, Axes property 2-327 XLimMode, Axes property 2-327 XLS files loading 2-4495 xlsfinfo 2-4493xlsread 2-4495 xlswrite 2-4505 XMinorGrid, Axes property 2-328 xmlread 2-4510 xmlwrite 2-4515xor 2-4516 XOR, printing 2-227 2-359 2-901 2-1269 2-1899 $2 cdot 1969 \ 2 cdot 2321 \ 2 cdot 2334 \ 2 cdot 2933 \ 2 cdot 3193 \ 2 cdot 3272$ 2-3436 2-3633 2-3667 2-3828 2-3851 2-3933 XScale, Axes property 2-328 xslt 2-4517 XTick, Axes property 2-328 XTickLabel, Axes property 2-329 XTickLabelMode, Axes property 2-330 XTickMode, Axes property 2-329 XVisual, Figure property 2-1460 XVisualMode, Figure property 2-1462 XWD files writing 2-2014 xyz coordinates. See Cartesian coordinates

Y

γ annotation arrow property 2-176 2-181 2-187 textarrow property 2-200 y-axis limits, setting and querying 2-4490 YAxisLocation, Axes property 2-324 YColor, Axes property 2-325 YData areaseries property 2-235 barseries property 2-367 contour property 2-912 errorbar property 2-1279 Image property 2-1974 Line property 2-2327 lineseries property 2-2342 Patch property 2-2946 quivergroup property 2-3205 scatter property 2-3445 stairseries property 2-3642 stem property 2-3676 Surface property 2-3838 surfaceplot property 2-3863 YDataMode contour property 2-912 quivergroup property 2-3205 surfaceplot property 2-3863 YDataSource areaseries property 2-236 barseries property 2-368 contour property 2-912 errorbar property 2-1280 lineseries property 2-2343 quivergroup property 2-3206 scatter property 2-3445 stairseries property 2-3642 stem property 2-3676 surfaceplot property 2-3863 YDir, Axes property 2-325 YGrid, Axes property 2-326 ylabel 2-4488

YLabel, Axes property 2-326 ylim 2-4490 YLim, Axes property 2-327 YLimMode, Axes property 2-327 YMinorGrid, Axes property 2-328 YScale, Axes property 2-328 YTick, Axes property 2-328 YTickLabel, Axes property 2-329 YTickLabelMode, Axes property 2-330 YTickMode, Axes property 2-329

Z

z-axis limits, setting and querying 2-4490
ZColor, Axes property 2-325
ZData

contour property 2-913
Line property 2-2327
lineseries property 2-2343
Patch property 2-2946
quivergroup property 2-3206
scatter property 2-3446
stemseries property 2-3677
Surface property 2-3838
surfaceplot property 2-3864

ZDataSource contour property 2-913 lineseries property 2-2343 2-3677 scatter property 2-3446 surfaceplot property 2-3864 ZDir, Axes property 2-325 zero of a function, finding 2-1638 zeros 2-4519 ZGrid, Axes property 2-326 Ziggurat 2-3225 2-3229 zip 2-4521 zlabel 2-4488 zlim 2-4490 ZLim, Axes property 2-327 ZLimMode, Axes property 2-327 ZMinorGrid, Axes property 2-328 zoom 2-4524zoom mode objects 2-4525 ZScale, Axes property 2-328 ZTick, Axes property 2-328 ZTickLabel, Axes property 2-329 ZTickLabelMode, Axes property 2-330 ZTickMode, Axes property 2-329