


**MATLAB<sup>®</sup>**

External Interfaces



**MATLAB<sup>®</sup>**

R2016b



## How to Contact MathWorks



Latest news: [www.mathworks.com](http://www.mathworks.com)  
Sales and services: [www.mathworks.com/sales\\_and\\_services](http://www.mathworks.com/sales_and_services)  
User community: [www.mathworks.com/matlabcentral](http://www.mathworks.com/matlabcentral)  
Technical support: [www.mathworks.com/support/contact\\_us](http://www.mathworks.com/support/contact_us)



Phone: 508-647-7000



The MathWorks, Inc.  
3 Apple Hill Drive  
Natick, MA 01760-2098

*MATLAB<sup>®</sup> External Interfaces*

© COPYRIGHT 1984–2016 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

**FEDERAL ACQUISITION:** This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

### **Trademarks**

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See [www.mathworks.com/trademarks](http://www.mathworks.com/trademarks) for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

### **Patents**

MathWorks products are protected by one or more U.S. patents. Please see [www.mathworks.com/patents](http://www.mathworks.com/patents) for more information.

## Revision History

December 1996	First printing	New for MATLAB 5 (release 8)
July 1997	Online only	Revised for MATLAB 5.1 (Release 9)
January 1998	Second printing	Revised for MATLAB 5.2 (Release 10)
October 1998	Third printing	Revised for MATLAB 5.3 (Release 11)
November 2000	Fourth printing	Revised and renamed for MATLAB 6.0 (Release 12)
June 2001	Online only	Revised for MATLAB 6.1 (Release 12.1)
July 2002	Online only	Revised for MATLAB 6.5 (Release 13)
January 2003	Online only	Revised for MATLAB 6.5.1 (Release 13SP1)
June 2004	Online only	Revised for MATLAB 7.0 (Release 14)
October 2004	Online only	Revised for MATLAB 7.0.1 (Release 14SP1)
September 2005	Online only	Revised for MATLAB 7.1 (Release 14SP3)
March 2006	Online only	Revised for MATLAB 7.2 (Release 2006a)
September 2006	Online only	Revised for MATLAB 7.3 (Release 2006b)
March 2007	Online only	Revised for MATLAB 7.4 (Release 2007a)
September 2007	Online only	Revised for MATLAB 7.5 (Release 2007b)
March 2008	Online only	Revised for MATLAB 7.6 (Release 2008a)
October 2008	Online only	Revised for MATLAB 7.7 (Release 2008b)
March 2009	Online only	Revised for MATLAB 7.8 (Release 2009a)
September 2009	Online only	Revised for MATLAB 7.9 (Release 2009b)
March 2010	Online only	Revised for MATLAB 7.10 (Release 2010a)
September 2010	Online only	Revised for MATLAB 7.11 (Release 2010b)
April 2011	Online only	Revised for MATLAB 7.12 (Release 2011a)
September 2011	Online only	Revised for MATLAB 7.13 (Release 2011b)
March 2012	Online only	Revised for MATLAB 7.14 (Release 2012a)
September 2012	Online only	Revised for MATLAB 8.0 (Release 2012b)
March 2013	Online only	Revised for MATLAB 8.1 (Release 2013a)
September 2013	Online only	Revised for MATLAB 8.2 (Release 2013b)
March 2014	Online only	Revised for MATLAB 8.3 (Release 2014a)
October 2014	Online only	Revised for MATLAB 8.4 (Release 2014b)
March 2015	Online only	Revised for MATLAB 8.5 (Release 2015a)
September 2015	Online only	Revised for MATLAB 8.6 (Release 2015b)
March 2016	Online only	Revised for MATLAB 9.0 (Release 2016a)
September 2016	Online only	Revised for MATLAB 9.1 (Release 2016b)



## Python Interface Topics

<b>Install Supported Python Implementation</b> .....	<b>1-3</b>
Install Python Version 2.7 .....	<b>1-3</b>
Install Python Version 3.3, 3.4, or 3.5 .....	<b>1-3</b>
<b>Call Python from MATLAB</b> .....	<b>1-4</b>
<b>Call User-Defined Python Module</b> .....	<b>1-10</b>
<b>Use Python Numeric Types in MATLAB</b> .....	<b>1-12</b>
<b>Call Python Methods with Numeric Arguments</b> .....	<b>1-13</b>
<b>Default Numeric Types</b> .....	<b>1-14</b>
<b>Use Python <code>array</code> Types in MATLAB</b> .....	<b>1-15</b>
<b>Pass MATLAB Character Vector to Python Method</b> .....	<b>1-16</b>
<b>Use Python <code>str</code> Type in MATLAB</b> .....	<b>1-17</b>
<b>Pass MATLAB Backslash Control Character</b> .....	<b>1-18</b>
<b>Create Python <code>list</code> Variable</b> .....	<b>1-19</b>
<b>Use Python <code>list</code> Type in MATLAB</b> .....	<b>1-20</b>
<b>Use Python List of Numeric Types in MATLAB</b> .....	<b>1-22</b>
<b>Pass Cell Array as Python Sequence Type</b> .....	<b>1-23</b>
<b>Read Element of Nested <code>list</code> Type</b> .....	<b>1-25</b>

<b>Use Python tuple Type in MATLAB</b> .....	<b>1-26</b>
<b>Create Python tuple Variable</b> .....	<b>1-27</b>
<b>Create Singleton Python tuple Variable</b> .....	<b>1-28</b>
<b>Create Python dict Variable</b> .....	<b>1-29</b>
<b>Pass dict Argument to Python Method</b> .....	<b>1-30</b>
<b>Use Python dict Type in MATLAB</b> .....	<b>1-31</b>
<b>Convert Python dict Type to MATLAB Structure</b> .....	<b>1-33</b>
<b>Pass Keyword Arguments</b> .....	<b>1-34</b>
<b>Pass Python Function to Python map Function</b> .....	<b>1-35</b>
<b>Index into Python String</b> .....	<b>1-36</b>
<b>Index into Python List</b> .....	<b>1-37</b>
<b>Index into Python Tuple</b> .....	<b>1-39</b>
<b>Index into Python dict</b> .....	<b>1-40</b>
<b>Use Python List as Values in for Loop</b> .....	<b>1-41</b>
<b>Display Stepped Range of Elements</b> .....	<b>1-42</b>
<b>Access Elements in Python Container Types</b> .....	<b>1-43</b>
Sequence Types .....	<b>1-43</b>
Mapping Types .....	<b>1-44</b>
Size and Dimensions .....	<b>1-44</b>
Array Support .....	<b>1-45</b>
Use Zero-Based Indexing for Python Functions .....	<b>1-45</b>
<b>View Python Numeric Values</b> .....	<b>1-46</b>
Why Do I See Properties When I Display a Number? .....	<b>1-46</b>
What Is the L Character Attached to a Number? .....	<b>1-46</b>
<b>Call Methods on Python Variables</b> .....	<b>1-48</b>

<b>Reload Modified User-Defined Python Module</b> .....	<b>1-50</b>
<b>System and Configuration Requirements</b> .....	<b>1-52</b>
Python Version Support .....	<b>1-52</b>
Set Python Version on Windows Platform .....	<b>1-52</b>
Set Python Version on Mac and Linux Platforms .....	<b>1-53</b>
Download 64-bit Version of Python on Windows Platforms .	<b>1-53</b>
Requirements for Building Python Executable .....	<b>1-53</b>
<b>Create a Python Object</b> .....	<b>1-54</b>
<b>Pass Data to Python</b> .....	<b>1-57</b>
MATLAB Type to Python Type Mapping .....	<b>1-57</b>
MATLAB Vector to Python Mapping .....	<b>1-58</b>
<b>Unsupported MATLAB Types</b> .....	<b>1-59</b>
<b>Handle Data Returned from Python</b> .....	<b>1-60</b>
Automatic Python Type to MATLAB Type Mapping .....	<b>1-60</b>
Explicit Type Conversions .....	<b>1-60</b>
<b>How MATLAB Represents Python Operators</b> .....	<b>1-62</b>
<b>Execute Callable Python Object</b> .....	<b>1-64</b>
<b>Python import and MATLAB import Commands</b> .....	<b>1-65</b>
Do Not Type “import <i>pythonmodule</i> ” .....	<b>1-65</b>
Use MATLAB import to Shorten Class or Function Names .	<b>1-65</b>
<b>List, Tuple, and Dictionary Types</b> .....	<b>1-67</b>
<b>Limitations to Python Support</b> .....	<b>1-68</b>
<b>Limitations to Indexing into Python Objects</b> .....	<b>1-69</b>
<b>Undefined variable "py" or function "py.command"</b> .....	<b>1-70</b>
Python Not Installed .....	<b>1-70</b>
64-bit/32-bit Versions of Python on Windows Platforms . . . .	<b>1-70</b>
MATLAB Cannot Find Python .....	<b>1-70</b>
Error in User-Defined Python Module .....	<b>1-71</b>
Python Module Not on Python Search Path .....	<b>1-71</b>
Module Name Conflicts .....	<b>1-72</b>
Python Tries to Execute command in Wrong Module .....	<b>1-72</b>

<b>Help for Python Functions</b> .....	<b>1-73</b>
<b>Handle Python Exceptions</b> .....	<b>1-74</b>
<b>Troubleshooting Error Messages</b> .....	<b>1-75</b>
Python Error: Python class: message .....	<b>1-75</b>
Python Module Errors .....	<b>1-75</b>
Errors Converting Python Data .....	<b>1-76</b>
<b>Using Python Data in MATLAB</b> .....	<b>1-77</b>
<b>Call Python eval Function</b> .....	<b>1-78</b>
<b>Precedence Order of Methods and Functions</b> .....	<b>1-80</b>
<b>Python Function Arguments</b> .....	<b>1-81</b>
Positional Arguments .....	<b>1-81</b>
Keyword Arguments .....	<b>1-81</b>
Optional Arguments .....	<b>1-82</b>

## Read and Write MATLAB MAT-Files in C/C++ and Fortran

# 2

<b>Custom Applications to Access MAT-Files</b> .....	<b>2-2</b>
Why Write Custom Applications? .....	<b>2-2</b>
MAT-File Interface Library .....	<b>2-3</b>
Exchanging Data Files Between Platforms .....	<b>2-4</b>
<b>MAT-File Library and Include Files</b> .....	<b>2-5</b>
MAT-Function Include Files .....	<b>2-5</b>
MAT-Function Libraries .....	<b>2-5</b>
Example Files .....	<b>2-6</b>
<b>What You Need to Build Custom Applications</b> .....	<b>2-7</b>
<b>Copy External Data into MAT-File Format with Standalone Programs</b> .....	<b>2-8</b>
Overview of matimport.c Example .....	<b>2-8</b>
Declare Variables for External Data .....	<b>2-9</b>



Create mxArray Variables .....	2-9
Create MATLAB Variable Names .....	2-10
Read External Data into mxArray Data .....	2-10
Create and Open MAT-File .....	2-11
Write mxArray Data to File .....	2-11
Clean Up .....	2-11
Build the Application .....	2-11
Create the MAT-File .....	2-11
Import Data into MATLAB .....	2-12
<b>Create MAT-File in C or C++ .....</b>	<b>2-13</b>
Create MAT-File in C .....	2-13
Create MAT-File in C++ .....	2-13
<b>Read MAT-File in C/C++ .....</b>	<b>2-14</b>
<b>Create MAT-File in Fortran .....</b>	<b>2-15</b>
<b>Read MAT-File in Fortran .....</b>	<b>2-16</b>
<b>Work with mxArrays .....</b>	<b>2-17</b>
Read Structures from a MAT-File .....	2-17
Read Cell Arrays from a MAT-File .....	2-18
<b>Table of MAT-File Source Code Files .....</b>	<b>2-19</b>
<b>Build on Mac and Linux Operating Systems .....</b>	<b>2-21</b>
Setting Run-Time Library Path .....	2-21
Building the Application .....	2-22
<b>Build on Windows Operating Systems .....</b>	<b>2-23</b>
<b>Share MAT-File Applications .....</b>	<b>2-24</b>

## Calling C Shared Library Functions from MATLAB

### 3

<b>Call Functions in Shared Libraries .....</b>	<b>3-2</b>
What Is a Shared Library? .....	3-2
Load and Unload Library .....	3-3

View Library Functions .....	3-4
Invoke Library Functions .....	3-6
<b>Limitations to Shared Library Support .....</b>	<b>3-8</b>
MATLAB Supports C Library Routines .....	3-8
Workarounds for Loading C++ Libraries .....	3-8
Limitations Using printf Function .....	3-9
Bit Fields .....	3-9
Enum Declarations .....	3-10
Unions Not Supported .....	3-10
Compiler Dependencies .....	3-11
Limitations Using Pointers .....	3-11
Functions with Variable Number of Input Arguments Not Supported .....	3-12
<b>Limitations Using Structures .....</b>	<b>3-13</b>
MATLAB Returns Pointers to Structures .....	3-13
Structure Cannot Contain Pointers to Other Structures ...	3-13
Requirements for MATLAB Structure Arguments .....	3-13
Requirements for C struct Field Names .....	3-13
<b>Module Not Found Error .....</b>	<b>3-15</b>
<b>No Matching Signature Error .....</b>	<b>3-16</b>
<b>MATLAB Terminates Unexpectedly When Calling Function in Shared Library .....</b>	<b>3-17</b>
<b>Pass Arguments to Shared Library Functions .....</b>	<b>3-18</b>
C and MATLAB Equivalent Types .....	3-18
How MATLAB Displays Function Signatures .....	3-20
NULL Pointer .....	3-21
Manually Convert Data Passed to Functions .....	3-21
<b>Shared Library <code>shrlibsample</code> .....</b>	<b>3-23</b>
<b>Pass String Arguments .....</b>	<b>3-24</b>
stringToUpper Function .....	3-24
Convert MATLAB Character Array to Uppercase .....	3-24
<b>Pass Structures .....</b>	<b>3-26</b>
addStructFields and addStructByRef Functions .....	3-26
Add Values of Fields in Structure .....	3-27

Preconvert MATLAB Structure Before Adding Values . . . . .	3-28
Autoconvert Structure Arguments . . . . .	3-29
Pass Pointer to Structure . . . . .	3-30
<b>Pass Enumerated Types . . . . .</b>	<b>3-32</b>
readEnum Function . . . . .	3-32
Display Enumeration Values . . . . .	3-32
<b>Pass Pointers . . . . .</b>	<b>3-34</b>
multDoubleRef Function . . . . .	3-34
Pass Pointer of Type double . . . . .	3-34
Create Pointer Offset from Existing lib.pointer Object . . . . .	3-35
Multilevel Pointers . . . . .	3-36
allocateStruct and deallocateStruct Functions . . . . .	3-36
Pass Multilevel Pointer . . . . .	3-37
Return Array of Strings . . . . .	3-37
<b>Pass Arrays . . . . .</b>	<b>3-39</b>
print2darray Function . . . . .	3-39
Convert MATLAB Array to C-Style Dimensions . . . . .	3-39
multDoubleArray Function . . . . .	3-40
Preserve 3-D MATLAB Array . . . . .	3-41
<b>Iterate Through an Array . . . . .</b>	<b>3-43</b>
Create Cell Array from lib.pointer Object . . . . .	3-43
Perform Pointer Arithmetic on Structure Array . . . . .	3-44
<b>Pointer Arguments . . . . .</b>	<b>3-46</b>
Pointer Arguments in C Functions . . . . .	3-46
Put String into Void Pointer . . . . .	3-46
Memory Allocation for External Library . . . . .	3-47
<b>Structure Arguments . . . . .</b>	<b>3-49</b>
Structure Argument Requirements . . . . .	3-49
Find Structure Field Names . . . . .	3-49
Strategies for Passing Structures . . . . .	3-49
<b>Explore libstruct Objects . . . . .</b>	<b>3-51</b>
<b>MATLAB Prototype Files . . . . .</b>	<b>3-52</b>
When to Use Prototype Files . . . . .	3-52
How to Create Prototype Files . . . . .	3-52
How to Specify Thunk Files . . . . .	3-53

Deploy Applications That Use <code>loadlibrary</code> .....	3-53
<code>loadlibrary</code> in Parallel Computing Environment .....	3-53
Change Function Signature .....	3-53
Rename Library Function .....	3-53
Load Subset of Functions in Library .....	3-53
Call Function with Variable Number of Arguments .....	3-54

## Intro to MEX-Files

# 4

<b>Introducing MEX Files</b> .....	4-3
<b>Using MEX Files</b> .....	4-4
<b>MEX File Placement</b> .....	4-5
MEX Files on Windows Network Drives .....	4-5
<b>Use Help Files with MEX Files</b> .....	4-6
<b>MATLAB Data</b> .....	4-7
The MATLAB Array .....	4-7
Lifecycle of <code>mxArray</code> .....	4-7
Data Storage .....	4-8
MATLAB Types .....	4-10
Sparse Matrices .....	4-11
Using Data Types .....	4-12
<b>Testing for Most-Derived Class</b> .....	4-15
Testing for a Category of Types .....	4-15
Another Test for Built-In Types .....	4-16
<b>Build MEX File</b> .....	4-17
<b>Linking Multiple Files</b> .....	4-18
<b>What You Need to Build MEX Files</b> .....	4-19
<b>Change Default Compiler</b> .....	4-20
Windows Systems .....	4-20
Change Linux System Default Compiler .....	4-21

Use Non-Default Compiler on Mac Systems .....	4-21
Do Not Use mex -f optionsfile Syntax .....	4-22
<b>SDK "macosx10.8" cannot be located Error Message .....</b>	<b>4-23</b>
<b>Custom Build with MEX Script Options .....</b>	<b>4-24</b>
Include Files .....	4-24
<b>Compiling MEX Files with the Microsoft Visual C++ IDE ..</b>	<b>4-25</b>
<b>Call LAPACK and BLAS Functions .....</b>	<b>4-26</b>
What You Need to Know .....	4-26
Creating a MEX File Using LAPACK and BLAS Functions .	4-26
Preserving Input Values from Modification .....	4-28
Passing Arguments to Fortran Functions from C/C++	
Programs .....	4-29
Passing Arguments to Fortran Functions from Fortran	
Programs .....	4-30
Handling Complex Numbers in LAPACK and BLAS	
Functions .....	4-31
Modifying the Function Name on UNIX Systems .....	4-34
<b>Upgrade MEX Files to Use 64-Bit API .....</b>	<b>4-35</b>
MATLAB Support for 64-Bit Indexing .....	4-35
MEX Uses 32-Bit API by Default .....	4-35
What If I Do Not Upgrade? .....	4-37
How to Upgrade MEX-Files to Use the 64-Bit API .....	4-37
<b>Upgrade MEX Files to Use Graphics Objects .....</b>	<b>4-46</b>
Replace mexGet and mexSet Functions .....	4-46
mex Automatically Converts Handle Type .....	4-49
I Want to Rebuild MEX Source Code Files .....	4-49
I Do Not Have MEX Source Code File .....	4-49
<b>Platform Compatibility .....</b>	<b>4-51</b>
<b>Invalid MEX File Error .....</b>	<b>4-52</b>
<b>Run MEX File You Receive from Someone Else .....</b>	<b>4-53</b>
<b>MEX File Dependent Libraries .....</b>	<b>4-54</b>
<b>Document Build Information in the MEX File .....</b>	<b>4-55</b>

<b>Version Compatibility</b> .....	<b>4-57</b>
<b>Getting Help When MEX Fails</b> .....	<b>4-58</b>
Errors Finding Supported Compiler .....	4-58
Errors Building MEX Function .....	4-58
Preview mex Build Commands .....	4-59
<b>Compiling MEX File Fails</b> .....	<b>4-60</b>
Build Example Files .....	4-60
Use Supported Compiler .....	4-60
File Not Found on Windows .....	4-60
Linux gcc -fPIC Errors .....	4-60
Compiler Errors in Fortran MEX Files .....	4-60
Syntax Errors Compiling C/C++ MEX Files on UNIX .....	4-60
<b>Symbol mexFunction Unresolved or Not Defined</b> .....	<b>4-62</b>
<b>MEX File Segmentation Fault</b> .....	<b>4-63</b>
<b>MEX File Generates Incorrect Results</b> .....	<b>4-64</b>
<b>Memory Management Issues</b> .....	<b>4-65</b>
Overview .....	4-65
Improperly Destroying an mxArray .....	4-66
Incorrectly Constructing a Cell or Structure mxArray .....	4-66
Creating a Temporary mxArray with Improper Data .....	4-67
Creating Potential Memory Leaks .....	4-68
Improperly Destroying a Structure .....	4-68
Destroying Memory in a C++ Class Destructor .....	4-69

## C/C++ MEX-Files

# 5

<b>Components of MEX File</b> .....	<b>5-3</b>
mexFunction Gateway Routine .....	5-3
Naming the MEX File .....	5-3
Required Parameters .....	5-3
Managing Input and Output Parameters .....	5-4
Validating Inputs .....	5-4
Computational Routine .....	5-5

<b>MATLAB API Libraries</b> .....	<b>5-6</b>
Matrix Library .....	<b>5-6</b>
MEX Library .....	<b>5-6</b>
Preprocessor Macros .....	<b>5-6</b>
<b>User Messages</b> .....	<b>5-8</b>
<b>Error Handling</b> .....	<b>5-9</b>
<b>Data Flow in MEX Files</b> .....	<b>5-10</b>
Showing Data Input and Output .....	<b>5-10</b>
Gateway Routine Data Flow Diagram .....	<b>5-11</b>
<b>Creating C++ MEX Files</b> .....	<b>5-13</b>
Creating Your C++ Source File .....	<b>5-13</b>
Compiling and Linking .....	<b>5-13</b>
Memory Considerations for Class Destructors .....	<b>5-13</b>
Use mexPrintf to Print to MATLAB Command Window ...	<b>5-14</b>
<b>C++ Class in MEX Files</b> .....	<b>5-15</b>
<b>Handle Files with C++</b> .....	<b>5-16</b>
C++ Example .....	<b>5-16</b>
C Example .....	<b>5-16</b>
<b>Create C Source MEX File</b> .....	<b>5-18</b>
<b>Table of MEX File Source Code Files</b> .....	<b>5-24</b>
<b>Choose a C++ Compiler</b> .....	<b>5-29</b>
Select Microsoft Visual Studio Compiler .....	<b>5-29</b>
Select MinGW-w64 Compiler .....	<b>5-29</b>
<b>Set Up C/C++ Examples</b> .....	<b>5-31</b>
<b>Pass Scalar Values</b> .....	<b>5-32</b>
Pass Scalar as Matrix .....	<b>5-32</b>
Pass Scalar by Value .....	<b>5-33</b>
<b>Pass Strings</b> .....	<b>5-35</b>
<b>Handling Strings in C/C++</b> .....	<b>5-37</b>
How MATLAB Represents Strings in MEX Files .....	<b>5-37</b>

Character Encoding and Multibyte Encoding Schemes . . . .	5-37
Converting MATLAB Character Vector to C-Style String . .	5-38
Converting C-Style String to MATLAB Character Vector . .	5-38
Returning Modified Input String . . . . .	5-38
Memory Management . . . . .	5-38
<b>Pass Multiple Inputs or Outputs . . . . .</b>	<b>5-40</b>
<b>Pass Structures and Cell Arrays . . . . .</b>	<b>5-42</b>
<b>Create 2-D Cell Array . . . . .</b>	<b>5-43</b>
<b>Fill mxArray . . . . .</b>	<b>5-44</b>
Options . . . . .	5-44
Copying Data Directly into an mxArray . . . . .	5-44
Pointing to Data . . . . .	5-44
<b>Prompt User for Input . . . . .</b>	<b>5-46</b>
<b>Handle Complex Data . . . . .</b>	<b>5-47</b>
<b>Handle 8-, 16-, and 32-Bit Data . . . . .</b>	<b>5-48</b>
<b>Manipulate Multidimensional Numerical Arrays . . . . .</b>	<b>5-49</b>
<b>Handle Sparse Arrays . . . . .</b>	<b>5-51</b>
<b>Call MATLAB Functions from C/C++ MEX Files . . . . .</b>	<b>5-52</b>
<b>Debug on Microsoft Windows Platforms . . . . .</b>	<b>5-53</b>
Notes on Debugging . . . . .	5-54
<b>Debug on Linux Platforms . . . . .</b>	<b>5-55</b>
<b>Debug on Mac Platforms . . . . .</b>	<b>5-57</b>
Using Xcode . . . . .	5-57
Using LLDB . . . . .	5-59
<b>Handling Large mxArrays . . . . .</b>	<b>5-62</b>
Using the 64-Bit API . . . . .	5-62
Building the Binary MEX File . . . . .	5-64
Example . . . . .	5-64
Caution Using Negative Values . . . . .	5-64



Building Cross-Platform Applications .....	5-65
<b>Memory Management</b> .....	<b>5-66</b>
Automatic Cleanup of Temporary Arrays .....	5-66
Example .....	5-67
Persistent Arrays .....	5-67
<b>Handling Large File I/O</b> .....	<b>5-69</b>
Prerequisites to Using 64-Bit I/O .....	5-69
Specifying Constant Literal Values .....	5-71
Opening a File .....	5-71
Printing Formatted Messages .....	5-72
Replacing <code>fseek</code> and <code>ftell</code> with 64-Bit Functions .....	5-72
Determining the Size of an Open File .....	5-73
Determining the Size of a Closed File .....	5-74
<b>Install MinGW-w64 Compiler</b> .....	<b>5-75</b>
Building <code>yprime.c</code> Example .....	5-75
MinGW Installation Folder Cannot Contain Space .....	5-75
Updating MEX Files to Use MinGW Compiler .....	5-76
<b>Troubleshooting and Limitations Compiling C/C++ MEX Files with MinGW-w64</b> .....	<b>5-77</b>
Do Not Link to Library Files Compiled with Non-MinGW Compilers .....	5-77
MinGW Installation Folder Cannot Contain Space .....	5-77
MEX Command Does not Choose MinGW .....	5-78
Manually Configure MinGW for MATLAB .....	5-78
MinGW Behaves Similarly to <code>gcc/g++</code> on Linux .....	5-79
Potential Memory Leak Inside C++ MEX Files on Using MEX Exceptions .....	5-79
Unhandled Explicit Exceptions in C++ MEX Files Unexpectedly Terminate MATLAB .....	5-80
Out of Memory Error for Variables Containing Large Amounts of Data .....	5-81

<b>Components of Fortran MEX File</b> .....	6-2
mexFunction Gateway Routine .....	6-2
Naming the MEX File .....	6-2
Difference Between .f and .F Files .....	6-2
Required Parameters .....	6-3
Managing Input and Output Parameters .....	6-3
Validating Inputs .....	6-4
Computational Routine .....	6-4
<b>MATLAB Fortran API Libraries</b> .....	6-5
Matrix Library .....	6-5
MEX Library .....	6-5
Preprocessor Macros .....	6-5
Using the Fortran %val Construct .....	6-6
<b>Data Flow in Fortran MEX Files</b> .....	6-8
Showing Data Input and Output .....	6-8
Gateway Routine Data Flow Diagram .....	6-9
<b>User Messages</b> .....	6-11
<b>Error Handling</b> .....	6-12
<b>Build Fortran MEX File</b> .....	6-13
<b>Create Fortran Source MEX File</b> .....	6-14
<b>Set Up Fortran Examples</b> .....	6-19
<b>Pass Scalar Values</b> .....	6-20
<b>Pass Strings</b> .....	6-21
<b>Pass Arrays of Strings</b> .....	6-22
<b>Pass Matrices</b> .....	6-23
<b>Pass Integers</b> .....	6-24

<b>Pass Multiple Inputs or Outputs</b> .....	<b>6-25</b>
<b>Handle Complex Data</b> .....	<b>6-26</b>
<b>Dynamically Allocate Memory</b> .....	<b>6-27</b>
<b>Handle Sparse Matrices</b> .....	<b>6-28</b>
<b>Call MATLAB Functions from Fortran MEX Files</b> .....	<b>6-29</b>
<b>Debug Fortran Source MEX-Files</b> .....	<b>6-31</b>
Notes on Debugging .....	<b>6-31</b>
Debugging on Microsoft Windows Platforms .....	<b>6-31</b>
Debugging on Linux Platforms .....	<b>6-31</b>
<b>Handling Large mxArray</b> .....	<b>6-34</b>
Using the 64-Bit API .....	<b>6-34</b>
Building the Binary MEX File .....	<b>6-36</b>
Caution Using Negative Values .....	<b>6-36</b>
Building Cross-Platform Applications .....	<b>6-36</b>
<b>Memory Management</b> .....	<b>6-37</b>
<b>MATLAB Supports Fortran 77</b> .....	<b>6-38</b>

## Calling MATLAB Engine from C/C++ and Fortran Programs

# 7

<b>Introducing MATLAB Engine API for C/C++ and Fortran</b> ..	<b>7-2</b>
Communicating with MATLAB Software .....	<b>7-3</b>
<b>Callbacks in Applications</b> .....	<b>7-4</b>
<b>Call MATLAB Functions from C/C++ Applications</b> .....	<b>7-5</b>
<b>Call MATLAB Functions from Fortran Applications</b> .....	<b>7-7</b>
<b>Attach to Existing MATLAB Sessions</b> .....	<b>7-9</b>

<b>Build Windows Engine Application</b> .....	<b>7-11</b>
<b>Run Windows Engine Application</b> .....	<b>7-12</b>
<b>Set Run-Time Library Path on Windows Systems</b> .....	<b>7-13</b>
Change Path Each Time You Run the Application .....	<b>7-13</b>
Permanently Change Path .....	<b>7-13</b>
Troubleshooting .....	<b>7-14</b>
<b>Register MATLAB as a COM Server</b> .....	<b>7-15</b>
<b>Build Linux Engine Application</b> .....	<b>7-16</b>
<b>Build Mac OS X Engine Application</b> .....	<b>7-17</b>
<b>Run Linux Engine Application</b> .....	<b>7-18</b>
<b>Run Mac Engine Application</b> .....	<b>7-19</b>
<b>Set Run-Time Library Path on Linux Systems</b> .....	<b>7-20</b>
C Shell .....	<b>7-20</b>
Bourne Shell .....	<b>7-20</b>
<b>Set Run-Time Library Path on Mac Systems</b> .....	<b>7-21</b>
C Shell .....	<b>7-21</b>
Bourne Shell .....	<b>7-21</b>
<b>Build Engine Applications with IDE</b> .....	<b>7-23</b>
Configuring the IDE .....	<b>7-23</b>
Engine Include Files .....	<b>7-23</b>
Engine Libraries .....	<b>7-23</b>
Library Files Required by libeng .....	<b>7-24</b>
<b>Can't Start MATLAB Engine</b> .....	<b>7-26</b>
<b>Debug MATLAB Functions Used in Engine Applications</b> ..	<b>7-27</b>
<b>Multithreaded Applications</b> .....	<b>7-28</b>
<b>User Input Not Supported</b> .....	<b>7-29</b>
<b>Getting Started</b> .....	<b>7-30</b>

<b>MATLAB Engine API for Java</b> .....	8-2
<b>Build Java Engine Programs</b> .....	8-3
General Requirements .....	8-3
Compile and Run Java Code on Windows .....	8-3
Compile and Run Java Code on Macintosh .....	8-4
Compile and Run Java Code on Linux .....	8-5
<b>Java Example Source Code</b> .....	8-7
<b>Java Engine API Summary</b> .....	8-8
com.mathworks Packages .....	8-8
com.mathworks.engine.MatlabEngine Methods .....	8-8
java.util.concurrent.Future Interface .....	8-10
<b>Java Data Type Conversions</b> .....	8-11
Pass Java Data to MATLAB .....	8-11
Pass MATLAB Data to Java .....	8-11
<b>Start and Close MATLAB Session from Java</b> .....	8-13
Start MATLAB Synchronously .....	8-13
Start MATLAB Asynchronously .....	8-13
Start Engine with Startup Options .....	8-14
Close MATLAB Engine Session .....	8-15
<b>Connect Java to Running MATLAB Session</b> .....	8-16
Find and Connect to MATLAB .....	8-16
Connect to MATLAB Synchronously .....	8-16
Connect to MATLAB Asynchronously .....	8-17
Specify Name of Shared Session .....	8-17
<b>Execute MATLAB Functions from Java</b> .....	8-19
Calling MATLAB Functions .....	8-19
Execute Function with Single Returned Argument .....	8-19
Execute Function with Multiple Returned Arguments .....	8-20
When to Specify Number of Output Arguments .....	8-20
<b>Evaluate MATLAB Statements from Java</b> .....	8-22
Evaluating MATLAB Statements .....	8-22

Evaluate Mathematical Function in MATLAB .....	8-22
<b>Pass Variables from Java to MATLAB .....</b>	<b>8-24</b>
Ways to Pass Variables .....	8-24
Pass Function Arguments .....	8-24
Put Variables in the MATLAB Workspace .....	8-25
<b>Pass Variables from MATLAB to Java .....</b>	<b>8-26</b>
Coordinate Conversion .....	8-26
<b>Using Complex Variables in Java .....</b>	<b>8-27</b>
Complex Variables in MATLAB .....	8-27
Get Complex Variables from MATLAB .....	8-27
Pass Complex Variable to MATLAB Function .....	8-28
<b>Using MATLAB Structures in Java .....</b>	<b>8-29</b>
MATLAB Structures .....	8-29
Pass Struct to MATLAB Function .....	8-29
Get Struct from MATLAB .....	8-30
<b>Pass Java CellStr to MATLAB .....</b>	<b>8-32</b>
MATLAB Cell Arrays .....	8-32
Create CellStr .....	8-32
<b>Using MATLAB Handle Objects in Java .....</b>	<b>8-34</b>
MATLAB Handle Objects .....	8-34
Java HandleObject Class .....	8-34
Set Graphics Object Properties from Java .....	8-34
<b>Redirect MATLAB Command Window Output to Java ....</b>	<b>8-36</b>
Output to MATLAB Command Window .....	8-36
Redirect MATLAB Output .....	8-36
Redirect MATLAB Error Messages to Java .....	8-37
<b>Run Simulink Simulation from Java .....</b>	<b>8-38</b>
MATLAB Command to Run Simulation .....	8-38
Run vdp Model from Java .....	8-38
<b>MATLAB Engine API Exceptions .....</b>	<b>8-42</b>
com.mathworks.engine.EngineException .....	8-42
com.mathworks.engine.UnsupportedTypeException .	8-42
com.mathworks.engine.MatlabExecutionException .	8-42
com.mathworks.engine.MatlabSyntaxException ....	8-42

<b>Pass Java Array Arguments to MATLAB</b> .....	8-43
2-D Array Arguments for MATLAB Functions .....	8-43
Multidimensional Arrays .....	8-43
<b>Incorrect Java Data Types</b> .....	8-45
Java String to MATLAB Character Vector .....	8-45
Setting Graphics Object Properties from Java .....	8-46
Java Integer to MATLAB double .....	8-46
<b>Incorrect Number of Output Arguments</b> .....	8-47

## MATLAB Engine for Python Topics

# 9

<b>Get Started with MATLAB Engine API for Python</b> .....	9-2
<b>Install MATLAB Engine API for Python</b> .....	9-5
<b>Install MATLAB Engine API for Python in Nondefault Locations</b> .....	9-6
Build or Install in Nondefault Folders .....	9-6
Install Engine in Your Home Folder .....	9-7
<b>Start and Stop MATLAB Engine for Python</b> .....	9-8
Start MATLAB Engine for Python .....	9-8
Run Multiple Engines .....	9-8
Stop Engine .....	9-8
Start Engine with Startup Options .....	9-9
Start Engine Asynchronously .....	9-9
<b>Connect Python to Running MATLAB Session</b> .....	9-10
Connect to Shared MATLAB Session .....	9-10
Connect Asynchronously to Shared MATLAB Session .....	9-11
Connect to Multiple Shared MATLAB Sessions .....	9-11
Start Shared MATLAB Sessions with Startup Options .....	9-12
<b>Call MATLAB Functions from Python</b> .....	9-13
Return Output Argument from MATLAB Function .....	9-13
Return Multiple Output Arguments from MATLAB Function .....	9-13
Return No Output Arguments from MATLAB Function .....	9-13

Stop Execution of Function .....	9-14
<b>Call MATLAB Functions Asynchronously from Python ...</b>	<b>9-15</b>
<b>Call User Script and Function from Python .....</b>	<b>9-16</b>
<b>Redirect Standard Output and Error to Python .....</b>	<b>9-18</b>
<b>Use MATLAB Handle Objects in Python .....</b>	<b>9-19</b>
<b>Use MATLAB Engine Workspace in Python .....</b>	<b>9-21</b>
<b>Pass Data to MATLAB from Python .....</b>	<b>9-22</b>
Python Type to MATLAB Scalar Type Mapping .....	9-22
Python Container to MATLAB Array Type Mapping .....	9-22
Unsupported Python Types .....	9-23
<b>Handle Data Returned from MATLAB to Python .....</b>	<b>9-24</b>
MATLAB Scalar Type to Python Type Mapping .....	9-24
MATLAB Array Type to Python Type Mapping .....	9-25
Unsupported MATLAB Types .....	9-25
<b>MATLAB Arrays as Python Variables .....</b>	<b>9-27</b>
Create MATLAB Arrays in Python .....	9-27
MATLAB Array Attributes and Methods in Python .....	9-29
Multidimensional MATLAB Arrays in Python .....	9-29
Index Into MATLAB Arrays in Python .....	9-29
Slice MATLAB Arrays in Python .....	9-30
Reshape MATLAB Arrays in Python .....	9-31
<b>Use MATLAB Arrays in Python .....</b>	<b>9-32</b>
<b>Sort and Plot MATLAB Data from Python .....</b>	<b>9-34</b>
<b>Get Help for MATLAB Functions from Python .....</b>	<b>9-38</b>
How to Find MATLAB Help .....	9-38
Open MATLAB Help Browser from Python .....	9-38
Display MATLAB Help at Python Prompt .....	9-39
<b>Default Numeric Types in MATLAB and Python .....</b>	<b>9-40</b>
<b>System Requirements for MATLAB Engine API for Python</b>	<b>9-42</b>
Python Version Support .....	9-42



Download 64-Bit Versions of Python and MATLAB .....	9-43
Requirements for Building Python from Source .....	9-43
<b>Limitations to MATLAB Engine API for Python .....</b>	<b>9-44</b>
<b>Troubleshoot MATLAB Errors in Python .....</b>	<b>9-45</b>
MATLAB Errors in Python .....	9-45
MatlabExecutionError: Undefined Function .....	9-45
SyntaxError: Expression Not Valid Target .....	9-46
SyntaxError: Invalid Syntax .....	9-46
Cannot Find MATLAB Session in Python .....	9-47

## Using Java Libraries from MATLAB

# 10

<b>Call Method on Java Object .....</b>	<b>10-2</b>
<b>Java Libraries .....</b>	<b>10-3</b>
Java Software Is Integral to MATLAB .....	10-3
When to Use Java Libraries in MATLAB .....	10-3
To Learn More About Java Programming Language .....	10-4
Platform Support for JVM Software .....	10-4
<b>Bring Java Classes into MATLAB Workspace .....</b>	<b>10-5</b>
Introduction .....	10-5
Defining New Java Classes .....	10-5
Java Class Path .....	10-5
Making Java Classes Available in MATLAB Workspace ...	10-7
Loading Java Class Definitions .....	10-9
Simplifying Java Class Names Using import Function ...	10-9
Locating Native Method Libraries .....	10-10
<b>Convert Java String to Uppercase .....</b>	<b>10-12</b>
<b>Use Class in Java JAR File on Static Class Path .....</b>	<b>10-13</b>
<b>Call User-Defined Java Class on Dynamic Class Path ....</b>	<b>10-14</b>
<b>Java Objects .....</b>	<b>10-15</b>
Overview .....	10-15

Constructing Java Objects .....	10-15
Concatenating Java Objects .....	10-17
Saving and Loading Java Objects to MAT-Files .....	10-18
Finding the Public Data Fields of an Object .....	10-19
Accessing Private and Public Data .....	10-20
Determining the Class of an Object .....	10-21
<b>Java Object Methods .....</b>	<b>10-23</b>
Calling Syntax .....	10-23
Obtaining Method Information .....	10-25
Java Methods That Affect MATLAB Commands .....	10-28
How MATLAB Handles Undefined Methods .....	10-29
Handling Java Exceptions .....	10-30
Method Execution in MATLAB .....	10-30
<b>Java Arrays .....</b>	<b>10-31</b>
Introduction .....	10-31
How MATLAB Represents the Java Array .....	10-31
Creating an Array of Objects in MATLAB .....	10-35
Accessing Elements of a Java Array .....	10-38
Assigning to a Java Array .....	10-41
Concatenating Java Arrays .....	10-44
Creating a New Array Reference .....	10-45
Creating a Copy of a Java Array .....	10-46
<b>Read URL Using java.net.URL .....</b>	<b>10-48</b>
Overview .....	10-48
Description of URLdemo .....	10-48
Running the Example .....	10-49
<b>Find Internet Protocol Address Using java.net.InetAddress .....</b>	<b>10-50</b>
Overview .....	10-50
Description of resolveip .....	10-50
Run the Example .....	10-51
<b>Create and Use Phone Book Using Java Classes .....</b>	<b>10-53</b>
Overview .....	10-53
Description of Function phonebook .....	10-54
Description of Function pb_lookup .....	10-58
Description of Function pb_add .....	10-58
Description of Function pb_remove .....	10-59
Description of Function pb_change .....	10-60

Description of Function pb_listall .....	10-61
Description of Function pb_display .....	10-62
Description of Function pb_keyfilter .....	10-62
Running the phonebook Program .....	10-63
<b>Java Heap Memory Preferences .....</b>	<b>10-65</b>
<b>Pass Data to Java Methods .....</b>	<b>10-66</b>
Introduction .....	10-66
Conversion of MATLAB Argument Data .....	10-66
Passing Built-In Types .....	10-68
Converting Numbers to Integer Arguments .....	10-69
Passing String Arguments .....	10-70
Passing Java Objects .....	10-70
Other Data Conversion Topics .....	10-73
Passing Data to Overloaded Methods .....	10-74
<b>Handle Data Returned from Java Methods .....</b>	<b>10-76</b>
Introduction .....	10-76
Conversion of Java Return Types .....	10-76
Conversion of Java Object Return Types .....	10-77
Built-In Types .....	10-78
Converting Objects to MATLAB Types .....	10-78

## Using .NET Libraries from MATLAB

# 11

<b>Read Cell Arrays of Excel Spreadsheet Data .....</b>	<b>11-4</b>
<b>Access a Simple .NET Class .....</b>	<b>11-6</b>
System.DateTime Example .....	11-6
Create .NET Object From Constructor .....	11-7
View Information About .NET Object .....	11-7
Introduction to .NET Data Types .....	11-9
<b>Load a Global .NET Assembly .....</b>	<b>11-12</b>
<b>Work with Microsoft Excel Spreadsheets Using .NET .....</b>	<b>11-13</b>
<b>Work with Microsoft Word Documents Using .NET .....</b>	<b>11-15</b>

<b>Assembly is Library of .NET Classes</b> .....	11-16
<b>Limitations to .NET Support</b> .....	11-17
<b>System Requirements for Using MATLAB Interface to .NET</b> .....	11-19
MATLAB Configuration File .....	11-19
<b>Using .NET from MATLAB</b> .....	11-20
Benefits of the MATLAB .NET Interface .....	11-20
Why Use the MATLAB .NET Interface? .....	11-20
.NET Assembly Integration Using MATLAB Compiler SDK .....	11-21
To Learn More About the .NET Framework .....	11-21
<b>Using a .NET Object</b> .....	11-22
Creating a .NET Object .....	11-22
What Classes Are in a .NET Assembly? .....	11-22
Using the delete Function on a .NET Object .....	11-23
<b>Build a .NET Application for MATLAB Examples</b> .....	11-24
<b>Troubleshooting Security Policy Settings from Network Drives</b> .....	11-25
<b>.NET Terminology</b> .....	11-26
.NET Framework System Namespace .....	11-26
Reference Type Versus Value Type .....	11-26
<b>Simplify .NET Class Names</b> .....	11-27
<b>Use import in MATLAB Functions</b> .....	11-28
<b>Nested Classes</b> .....	11-29
<b>Handle .NET Exceptions</b> .....	11-30
<b>Pass Numeric Arguments</b> .....	11-31
Call .NET Methods with Numeric Arguments .....	11-31
Use .NET Numeric Types in MATLAB .....	11-31
<b>Pass System.String Arguments</b> .....	11-32
Call .NET Methods with System.String Arguments .....	11-32
Use System.String in MATLAB .....	11-32

<b>Pass System.Enum Arguments</b> .....	11-34
Call .NET Methods with System.Enum Arguments .....	11-34
Use System.Enum in MATLAB .....	11-35
<b>Pass System.Nullable Arguments</b> .....	11-36
<b>Pass Cell Arrays of .NET Data</b> .....	11-40
Example of Cell Arrays of .NET Data .....	11-40
Create a Cell Array for Each System.Object .....	11-41
Create MATLAB Variables from the .NET Data .....	11-41
Call MATLAB Functions with MATLAB Variables .....	11-41
<b>Pass Jagged Arrays</b> .....	11-43
Create System.Double .NET Jagged Array .....	11-43
Call .NET Method with System.String Jagged Array Arguments .....	11-43
Call .NET Method with Multidimensional Jagged Array Arguments .....	11-44
<b>Convert Nested System.Object Arrays</b> .....	11-46
<b>Pass Data to .NET Objects</b> .....	11-47
Pass Primitive .NET Types .....	11-47
Pass Cell Arrays .....	11-48
Pass Nonprimitive .NET Objects .....	11-49
Pass MATLAB Character Arrays .....	11-49
Pass System.Nullable Type .....	11-49
Pass NULL Values .....	11-50
Unsupported MATLAB Types .....	11-50
Choosing Method Signatures .....	11-50
Example — Choosing a Method Signature .....	11-51
Pass Arrays .....	11-52
Pass MATLAB Arrays as Jagged Arrays .....	11-53
<b>Handle Data Returned from .NET Objects</b> .....	11-54
.NET Type to MATLAB Type Mapping .....	11-54
How MATLAB Handles System.String .....	11-55
How MATLAB Handles System.__ComObject .....	11-56
How MATLAB Handles System.Nullable .....	11-57
How MATLAB Handles dynamic Type .....	11-58
How MATLAB Handles Jagged Arrays .....	11-58

<b>Use Arrays with .NET Applications</b> .....	11-59
Passing MATLAB Arrays to .NET .....	11-59
Accessing .NET Array Elements in MATLAB .....	11-59
Converting .NET Jagged Arrays to MATLAB Arrays .....	11-60
<b>Convert .NET Arrays to Cell Arrays</b> .....	11-61
Convert Nested System.Object Arrays .....	11-61
cell Function Syntax for System.Object[,] Arrays .....	11-62
<b>Limitations to Support of .NET Arrays</b> .....	11-64
<b>Set Static .NET Properties</b> .....	11-65
System.Environment.CurrentDirectory Example .....	11-65
Do Not Use ClassName.PropertyName Syntax for Static Properties .....	11-65
<b>Using .NET Properties</b> .....	11-67
How MATLAB Represents .NET Properties .....	11-67
How MATLAB Maps C# Property and Field Access Modifiers .....	11-67
<b>MATLAB Does Not Display Protected Properties</b> .....	11-69
<b>Work with .NET Methods Having Multiple Signatures</b> ...	11-70
Display Function Signature Example .....	11-71
<b>Call .NET Methods With <code>out</code> Keyword</b> .....	11-72
<b>Call .NET Methods With <code>ref</code> Keyword</b> .....	11-74
<b>Call .NET Methods With <code>params</code> Keyword</b> .....	11-76
<b>Call .NET Methods with Optional Arguments</b> .....	11-78
Skip Optional Arguments .....	11-78
Call Overloaded Methods .....	11-79
<b>Calling .NET Methods</b> .....	11-81
Calling Object Methods .....	11-81
Getting Method Information .....	11-81
C# Method Access Modifiers .....	11-81
VB.NET Method Access Modifiers .....	11-82
Reading Method Signatures .....	11-82

<b>Calling .NET Methods with Optional Arguments</b> .....	11-84
Skipping Optional Arguments .....	11-84
Determining Which Overloaded Method Is Invoked .....	11-84
Support for ByRef Attribute in VB.NET .....	11-84
<b>Calling .NET Extension Methods</b> .....	11-85
<b>Call .NET Properties That Take an Argument</b> .....	11-86
<b>How MATLAB Represents .NET Operators</b> .....	11-88
<b>Limitations to Support of .NET Methods</b> .....	11-89
Overloading MATLAB Functions .....	11-89
<b>Use .NET Events in MATLAB</b> .....	11-90
Monitor Changes to .TXT File .....	11-90
Monitor Changes to Windows Form ComboBox .....	11-90
<b>Call .NET Delegates in MATLAB</b> .....	11-93
Declare a Delegate in a C# Assembly .....	11-93
Load the Assembly Containing the Delegate into MATLAB .....	11-93
Select a MATLAB Function .....	11-93
Create an Instance of the Delegate in MATLAB .....	11-94
Invoke the Delegate Instance in MATLAB .....	11-94
<b>Create Delegates from .NET Object Methods</b> .....	11-95
<b>Create Delegate Instances Bound to .NET Methods</b> .....	11-96
Example — Create a Delegate Instance Associated with a .NET Object Instance Method .....	11-96
Example — Create a Delegate Instance Associated with a Static .NET Method .....	11-97
<b>.NET Delegates With out and ref Type Arguments</b> .....	11-98
<b>Combine and Remove .NET Delegates</b> .....	11-99
<b>.NET Delegates</b> .....	11-101
<b>Calling .NET Methods Asynchronously</b> .....	11-102
How MATLAB Handles Asynchronous Method Calls in .NET .....	11-102

Calling a Method Asynchronously Using a Callback When an Asynchronous Call Finishes .....	11-102
Calling a Method Asynchronously Without a Callback ...	11-104
Using EndInvoke With out and ref Type Arguments ...	11-105
Using Polling to Detect When Asynchronous Call Finishes	11-105
<b>Limitations to Support of .NET Events .....</b>	<b>11-106</b>
MATLAB Support of Standard Signature of an Event Handler Delegate .....	11-106
<b>Limitations to Support of .NET Delegates .....</b>	<b>11-107</b>
<b>Use Bit Flags with .NET Enumerations .....</b>	<b>11-108</b>
How MATLAB Supports Bit-Wise Operations on System.Enum .....	11-108
Creating .NET Enumeration Bit Flags .....	11-108
Removing a Flag from a Variable .....	11-109
Replacing a Flag in a Variable .....	11-109
Testing for Membership .....	11-110
<b>Read Special System Folder Path .....</b>	<b>11-112</b>
<b>.NET Enumerations in MATLAB .....</b>	<b>11-113</b>
<b>Default Methods for an Enumeration .....</b>	<b>11-114</b>
<b>NetDocEnum Example Assembly .....</b>	<b>11-116</b>
<b>Work with Members of a .NET Enumeration .....</b>	<b>11-117</b>
<b>Refer to a .NET Enumeration Member .....</b>	<b>11-119</b>
Using the Implicit Constructor .....	11-119
<b>Display .NET Enumeration Members as Character     Vectors .....</b>	<b>11-121</b>
<b>Convert .NET Enumeration Values to Type Double ....</b>	<b>11-122</b>
<b>Iterate Through a .NET Enumeration .....</b>	<b>11-123</b>
Information About System.Enum Methods .....	11-123
Display Enumeration Member Names .....	11-124



<b>Use .NET Enumerations to Test for Conditions</b> .....	11-125
Using Switch Statements .....	11-125
Using Relational Operations .....	11-125
<b>Underlying Enumeration Values</b> .....	11-127
<b>Limitations to Support of .NET Enumerations</b> .....	11-128
<b>Create .NET Collections</b> .....	11-129
<b>Convert .NET Collections to MATLAB Arrays</b> .....	11-131
<b>Create .NET Arrays of Generic Type</b> .....	11-132
<b>Display .NET Generic Methods Using Reflection</b> .....	11-133
showGenericMethods Function .....	11-133
Display Generic Methods in a Class .....	11-134
Display Generic Methods in a Generic Class .....	11-135
<b>.NET Generic Classes</b> .....	11-136
<b>Accessing Items in .NET Collections</b> .....	11-137
<b>Call .NET Generic Methods</b> .....	11-138
Using the NetDocGeneric Example .....	11-138
Invoke Generic Class Member Function .....	11-139
Invoke Static Generic Functions .....	11-139
Invoke Static Generic Functions of a Generic Class .....	11-139
Invoke Generic Functions of a Generic Class .....	11-140

## Using COM Objects from MATLAB

# 12

<b>MATLAB COM Integration</b> .....	12-2
Concepts and Terminology .....	12-2
COM Objects, Clients, and Servers .....	12-2
Interfaces .....	12-3
The MATLAB COM Client .....	12-3
The MATLAB COM Automation Server .....	12-4

<b>Registering Controls and Servers</b> .....	<b>12-5</b>
Accessing COM Controls Created with .NET .....	12-5
Verifying the Registration .....	12-5
<b>Getting Started with COM</b> .....	<b>12-7</b>
Creating an Instance of a COM Object .....	12-7
Getting Information About a Particular COM Control .....	12-7
Getting an Object's ProgID .....	12-8
Registering a Custom Control .....	12-8
<b>Use Internet Explorer in MATLAB Figure</b> .....	<b>12-10</b>
Techniques Demonstrated .....	12-10
Using the Figure to Access Properties .....	12-10
Complete Code Listing .....	12-11
Creating the Figure .....	12-12
Calculating the ActiveX Object Container Size .....	12-12
Automatic Resize .....	12-13
Selecting Graphics Objects .....	12-13
<b>Read Spreadsheet Data Using Excel as Automation</b>	
<b>Server</b> .....	<b>12-15</b>
Techniques Demonstrated .....	12-15
Using the UI .....	12-15
Complete Code Listing .....	12-16
Excel Spreadsheet Format .....	12-16
Excel Automation Server .....	12-17
Manipulating the Data in the MATLAB Workspace .....	12-18
The Plotter UI .....	12-18
Inserting MATLAB Graphs Into Excel Spreadsheets .....	12-20
<b>Supported Client/Server Configurations</b> .....	<b>12-22</b>
Introduction .....	12-22
MATLAB Client and In-Process Server .....	12-22
MATLAB Client and Out-of-Process Server .....	12-23
COM Implementations Supported by MATLAB Software ..	12-24
Client Application and MATLAB Automation Server .....	12-24
Client Application and MATLAB Engine Server .....	12-25

<b>Create COM Objects</b> .....	13-3
Creating the Server Process — An Overview .....	13-3
Creating an ActiveX Control .....	13-4
Creating a COM Server .....	13-9
<b>Handle COM Data in MATLAB</b> .....	13-12
Passing Data to COM Objects .....	13-12
Handling Data from COM Objects .....	13-14
Unsupported Types .....	13-15
Passing MATLAB Data to ActiveX Objects .....	13-15
Passing MATLAB SAFEARRAY to COM Object .....	13-15
Reading SAFEARRAY from COM Objects in MATLAB Applications .....	13-17
Displaying MATLAB Syntax for COM Objects .....	13-18
<b>COM Object Properties</b> .....	13-21
MATLAB Functions for Object Properties .....	13-21
Work with Multiple Objects .....	13-21
Enumerated Values for Properties .....	13-22
Property Inspector .....	13-22
Custom Properties .....	13-23
Properties That Take Arguments .....	13-23
<b>COM Methods</b> .....	13-24
Getting Method Information .....	13-24
Calling Object Methods .....	13-24
Specifying Enumerated Parameters .....	13-25
Skipping Optional Input Arguments .....	13-25
Returning Multiple Output Arguments .....	13-26
<b>COM Events</b> .....	13-27
<b>COM Event Handlers</b> .....	13-29
Overview of Event Handling .....	13-29
Arguments Passed to Event Handlers .....	13-29
Event Structure .....	13-30
<b>COM Object Interfaces</b> .....	13-32
IUnknown and IDispatch Interfaces .....	13-32

Custom Interfaces .....	13-33
<b>Save and Delete COM Objects .....</b>	<b>13-35</b>
Functions for Saving and Restoring COM Objects .....	13-35
Releasing COM Interfaces and Objects .....	13-35
<b>MATLAB Application as DCOM Client .....</b>	<b>13-37</b>
<b>Explore COM Objects .....</b>	<b>13-38</b>
Exploring Properties .....	13-38
Exploring Methods .....	13-39
Exploring Events .....	13-39
Exploring Interfaces .....	13-40
Identifying Objects and Interfaces .....	13-40
<b>Change Row Height in Range of Spreadsheet Cells .....</b>	<b>13-42</b>
<b>Write Data to Excel Spreadsheet Using ActiveX .....</b>	<b>13-44</b>
<b>Change Cursor in Spreadsheet .....</b>	<b>13-46</b>
<b>Insert Spreadsheet After First Sheet .....</b>	<b>13-47</b>
<b>Redraw Circle in mwsamp Control .....</b>	<b>13-48</b>
<b>Connect to Existing Excel Application .....</b>	<b>13-50</b>
<b>Display Message for Workbook OnClose Event .....</b>	<b>13-51</b>
<b>Combine Event Handlers as MATLAB Local Functions ..</b>	<b>13-52</b>
<b>MATLAB Sample ActiveX Control mwsamp .....</b>	<b>13-53</b>
<b>Display Event Messages from mwsamp Control .....</b>	<b>13-54</b>
<b>Add Position Property to mwsamp Control .....</b>	<b>13-57</b>
<b>Save mwsamp2 COM Control .....</b>	<b>13-58</b>
<b>Deploy ActiveX Controls Requiring Run-Time Licenses ..</b>	<b>13-59</b>
Create Function to Build Control .....	13-59
Build Control and License File .....	13-59

Build Executable .....	13-60
Deploy Files .....	13-60
<b>Microsoft Forms 2.0 Controls .....</b>	<b>13-61</b>
Affected Controls .....	13-61
Replacement Controls .....	13-61
<b>COM Collections .....</b>	<b>13-63</b>
<b>MATLAB COM Support Limitations .....</b>	<b>13-64</b>
<b>Interpreting Argument Callouts in COM Error Messages ..</b>	<b>13-65</b>

## MATLAB COM Automation Server Support

# 14

<b>Register MATLAB as Automation Server .....</b>	<b>14-2</b>
When to Register MATLAB .....	14-2
Register from System Prompt .....	14-2
Register from MATLAB Command Prompt .....	14-3
<b>MATLAB COM Automation Server Interface .....</b>	<b>14-4</b>
COM Server Types .....	14-4
Shared and Dedicated Servers .....	14-4
Programmatic Identifiers .....	14-4
In-Process and Out-of-Process Servers .....	14-5
<b>Create MATLAB Server .....</b>	<b>14-7</b>
Getting Started .....	14-7
Get or Set the Status of a MATLAB Automation Server ...	14-8
<b>Connect to Existing MATLAB Server .....</b>	<b>14-9</b>
Using Visual Basic .NET Code .....	14-9
<b>MATLAB Application as DCOM Server .....</b>	<b>14-10</b>
<b>VT_DATE Data Type .....</b>	<b>14-11</b>
<b>Data Types For Visual Basic .NET Clients .....</b>	<b>14-12</b>

<b>Visible Property</b> .....	<b>14-13</b>
<b>Shared or Dedicated Server</b> .....	<b>14-14</b>
Starting a Shared Server .....	14-14
Starting a Dedicated Server .....	14-14
<b>Manually Create Automation Server</b> .....	<b>14-15</b>
<b>Launch MATLAB as Automation Server in Desktop Mode</b>	<b>14-16</b>
<b>Call MATLAB Function from Visual Basic .NET Client</b> ...	<b>14-17</b>
<b>Pass Complex Data to MATLAB from C# Client</b> .....	<b>14-18</b>
<b>Call MATLAB Function from C# Client</b> .....	<b>14-20</b>
<b>View MATLAB Functions from Visual Basic .NET Object Browser</b> .....	<b>14-22</b>
<b>Waiting for MATLAB Application to Complete</b> .....	<b>14-23</b>
<b>Conversion of MATLAB Types to COM Types</b> .....	<b>14-24</b>
Variant Data .....	14-25
SAFEARRAY Data .....	14-25
<b>Conversion of COM Types to MATLAB Types</b> .....	<b>14-26</b>

## Using Web Services with MATLAB

# 15

<b>Send and Receive HTTP Messages</b> .....	<b>15-2</b>
<b>What Is the HTTP Interface?</b> .....	<b>15-5</b>
<b>Manage Cookies</b> .....	<b>15-6</b>
<b>RequestMessage complete method</b> .....	<b>15-8</b>

<b>HTTP Data Type Conversion</b> .....	<b>15-9</b>
Converting Data in Request Messages .....	15-9
Converting Data in Response Messages .....	15-13
Supported Image Data Subtypes .....	15-15
<b>Display Progress Monitor for HTTP Message</b> .....	<b>15-17</b>
<b>Set Up WSDL Tools</b> .....	<b>15-21</b>
<b>Display a World Map</b> .....	<b>15-22</b>
<b>Using WSDL Web Service with MATLAB</b> .....	<b>15-27</b>
What Are Web Services in MATLAB? .....	15-27
What are WSDL Documents? .....	15-27
What You Need to Use WSDL with MATLAB .....	15-28
<b>Access Services That Use WSDL Documents</b> .....	<b>15-29</b>
<b>Error Handling</b> .....	<b>15-31</b>
Considerations Using Web Services .....	15-31
Error Handling with try/catch Statements .....	15-31
Use a Local Copy of the WSDL Document .....	15-31
Java Errors Accessing Service .....	15-32
Anonymous Types Not Supported .....	15-32
<b>XML-MATLAB Data Type Conversion</b> .....	<b>15-33</b>
<b>Limitations to WSDL Document Support</b> .....	<b>15-35</b>

## System Commands

# 16

<b>Shell Escape Functions</b> .....	<b>16-2</b>
<b>Run External Commands, Scripts, and Programs</b> .....	<b>16-3</b>
Run UNIX Programs off System Path .....	16-4
<b>Change Environment Variable for Shell Command</b> .....	<b>16-6</b>

<b>Capabilities and Supported Interfaces and Platforms . . . .</b>	<b>17-2</b>
What Is the MATLAB Serial Port Interface? . . . . .	17-2
Supported Serial Port Interface Standards . . . . .	17-3
Supported Platforms . . . . .	17-3
Using the Examples with Your Device . . . . .	17-3
<b>Overview of the Serial Port . . . . .</b>	<b>17-4</b>
Introduction . . . . .	17-4
What Is Serial Communication? . . . . .	17-4
The Serial Port Interface Standard . . . . .	17-4
Connecting Two Devices with a Serial Cable . . . . .	17-5
Serial Port Signals and Pin Assignments . . . . .	17-6
Serial Data Format . . . . .	17-10
Finding Serial Port Information for Your Platform . . . . .	17-13
Using Virtual USB Serial Ports . . . . .	17-15
Selected Bibliography . . . . .	17-15
<b>Getting Started with Serial I/O . . . . .</b>	<b>17-16</b>
Example: Getting Started . . . . .	17-16
The Serial Port Session . . . . .	17-16
Configuring and Returning Properties . . . . .	17-17
<b>Create a Serial Port Object . . . . .</b>	<b>17-22</b>
Overview of a Serial Port Object . . . . .	17-22
Configuring Properties During Object Creation . . . . .	17-23
The Serial Port Object Display . . . . .	17-24
Creating an Array of Serial Port Objects . . . . .	17-24
<b>Connect to the Device . . . . .</b>	<b>17-26</b>
<b>Configure Communication Settings . . . . .</b>	<b>17-27</b>
<b>Write and Read Data . . . . .</b>	<b>17-28</b>
Before You Begin . . . . .	17-28
Example — Introduction to Writing and Reading Data . . . . .	17-28
Controlling Access to the MATLAB Command Line . . . . .	17-29
Writing Data . . . . .	17-30
Reading Data . . . . .	17-35
Example — Writing and Reading Text Data . . . . .	17-41



Example — Parsing Input Data Using textscan . . . . .	17-42
Example — Reading Binary Data . . . . .	17-43
<b>Events and Callbacks . . . . .</b>	<b>17-46</b>
Introduction . . . . .	17-46
Example — Introduction to Events and Callbacks . . . . .	17-46
Event Types and Callback Properties . . . . .	17-47
Respond To Event Information . . . . .	17-49
Create and Execute Callback Functions . . . . .	17-51
Enable Callback Functions After They Error . . . . .	17-52
Example — Using Events and Callbacks . . . . .	17-52
<b>Control Pins . . . . .</b>	<b>17-54</b>
Properties of Serial Port Control Pins . . . . .	17-54
Signaling the Presence of Connected Devices . . . . .	17-54
Controlling the Flow of Data: Handshaking . . . . .	17-57
<b>Debugging: Recording Information to Disk . . . . .</b>	<b>17-60</b>
Introduction . . . . .	17-60
Recording Properties . . . . .	17-60
Example: Introduction to Recording Information . . . . .	17-61
Creating Multiple Record Files . . . . .	17-61
Specifying a Filename . . . . .	17-61
The Record File Format . . . . .	17-62
Example: Recording Information to Disk . . . . .	17-63
<b>Save and Load . . . . .</b>	<b>17-66</b>
Using save and load . . . . .	17-66
Using Serial Port Objects on Different Platforms . . . . .	17-66
<b>Disconnect and Clean Up . . . . .</b>	<b>17-68</b>
Disconnect a Serial Port Object . . . . .	17-68
Clean Up the MATLAB Environment . . . . .	17-68
<b>Property Reference . . . . .</b>	<b>17-70</b>
The Property Reference Page Format . . . . .	17-70
Serial Port Object Properties . . . . .	17-70
<b>Properties — Alphabetical List . . . . .</b>	<b>17-74</b>

<b>Support Package Installation</b> .....	18-2
What Is a Support Package? .....	18-2
Install Support Packages .....	18-2
<b>Support Package Installer Help</b> .....	18-3
About Support Package Installer .....	18-3
Select an Action .....	18-4
Select Support Package to Install or Select Support Package to Download .....	18-5
Log In to MathWorks Account .....	18-8
The MathWorks, Inc. Software License Agreement .....	18-10
Third-Party Software Licenses .....	18-11
Confirm Installation, Confirm Download, Confirm Uninstall .....	18-12
Install or Update Complete, Download Complete, Uninstall Complete .....	18-13
Set Up Support Package .....	18-14
Support Package Setup Complete .....	18-16
Special Instructions .....	18-16
<b>MATLAB Supported Hardware</b> .....	18-17
<b>Change Your Support Package Directory</b> .....	18-18

# Python Interface Topics

---

- “Install Supported Python Implementation” on page 1-3
- “Call Python from MATLAB” on page 1-4
- “Call User-Defined Python Module” on page 1-10
- “Use Python Numeric Types in MATLAB” on page 1-12
- “Call Python Methods with Numeric Arguments” on page 1-13
- “Default Numeric Types” on page 1-14
- “Use Python `array` Types in MATLAB” on page 1-15
- “Pass MATLAB Character Vector to Python Method” on page 1-16
- “Use Python `str` Type in MATLAB” on page 1-17
- “Pass MATLAB Backslash Control Character” on page 1-18
- “Create Python `list` Variable” on page 1-19
- “Use Python `list` Type in MATLAB” on page 1-20
- “Use Python List of Numeric Types in MATLAB” on page 1-22
- “Pass Cell Array as Python Sequence Type” on page 1-23
- “Read Element of Nested `list` Type” on page 1-25
- “Use Python `tuple` Type in MATLAB” on page 1-26
- “Create Python `tuple` Variable” on page 1-27
- “Create Singleton Python `tuple` Variable” on page 1-28
- “Create Python `dict` Variable” on page 1-29
- “Pass `dict` Argument to Python Method” on page 1-30
- “Use Python `dict` Type in MATLAB” on page 1-31
- “Convert Python `dict` Type to MATLAB Structure” on page 1-33
- “Pass Keyword Arguments” on page 1-34
- “Pass Python Function to Python `map` Function” on page 1-35
- “Index into Python String” on page 1-36

- “Index into Python List” on page 1-37
- “Index into Python Tuple” on page 1-39
- “Index into Python dict” on page 1-40
- “Use Python List as Values in for Loop” on page 1-41
- “Display Stepped Range of Elements” on page 1-42
- “Access Elements in Python Container Types” on page 1-43
- “View Python Numeric Values” on page 1-46
- “Call Methods on Python Variables” on page 1-48
- “Reload Modified User-Defined Python Module” on page 1-50
- “System and Configuration Requirements” on page 1-52
- “Create a Python Object” on page 1-54
- “Pass Data to Python” on page 1-57
- “Unsupported MATLAB Types” on page 1-59
- “Handle Data Returned from Python” on page 1-60
- “How MATLAB Represents Python Operators” on page 1-62
- “Execute Callable Python Object” on page 1-64
- “Python import and MATLAB import Commands” on page 1-65
- “List, Tuple, and Dictionary Types” on page 1-67
- “Limitations to Python Support” on page 1-68
- “Limitations to Indexing into Python Objects” on page 1-69
- “Undefined variable "py" or function "py.command"” on page 1-70
- “Help for Python Functions” on page 1-73
- “Handle Python Exceptions” on page 1-74
- “Troubleshooting Error Messages” on page 1-75
- “Using Python Data in MATLAB” on page 1-77
- “Call Python eval Function” on page 1-78
- “Precedence Order of Methods and Functions” on page 1-80
- “Python Function Arguments” on page 1-81

## Install Supported Python Implementation

### In this section...

“Install Python Version 2.7” on page 1-3

“Install Python Version 3.3, 3.4, or 3.5” on page 1-3

### Install Python Version 2.7

- Access <https://www.python.org/downloads> and scroll down to the **Looking for a specific release** section.
- Find the 2.7 version you want and click Download.
- Click the format you want, and follow the online instructions.

---

**Note:** For 64-bit MATLAB<sup>®</sup> on Microsoft<sup>®</sup> Windows<sup>®</sup> systems, select the 64-bit Python version, called Windows x86-64 MSI installer.

---

### Install Python Version 3.3, 3.4, or 3.5

- Access <https://www.python.org/downloads> and scroll down to the **Looking for a specific release** section.
- Find the 3.3/3.4/3.5 version you want and click Download.
- Click the format you want, and follow the online instructions.

---

**Note:** For 64-bit MATLAB on Windows systems, select the 64-bit Python version, called Windows x86-64 MSI installer.

---

### See Also

pyversion

### More About

- “MATLAB Cannot Find Python” on page 1-70
- “System and Configuration Requirements” on page 1-52

## Call Python from MATLAB

These examples show how to use Python® language functions and modules within MATLAB®. The first example calls a text-formatting module from the Python standard library. The second example shows how to use a third-party module, Beautiful Soup. If you want to run that example, follow the guidelines in the step for installing the module.

MATLAB supports the reference implementation of Python, often called CPython, versions 2.7, 3.3, and 3.4. If you are on a Mac or Linux platform, you already have Python installed. If you are on Windows, you need to install a distribution, such as those found at <https://www.python.org/download>, if you have not already done so. For more information, see “Install Supported Python Implementation”.

### Call a Python Function to Wrap Text in a Paragraph

MATLAB has equivalencies for much of the Python standard library, but not everything. For example, `textwrap` is a module for formatting blocks of text with carriage returns and other conveniences. MATLAB also provides a `textwrap` function, but it only wraps text to fit inside a UI control.

Create a paragraph of text to play with.

```
T = 'MATLAB(R) is a high-level language and interactive environment for numerical comp
```

### Convert a Python String to a MATLAB String

Call the `textwrap.wrap` function by typing the characters `py.` in front of the function name. Do not type `import textwrap`.

```
wrapped = py.textwrap.wrap(T);  
whos wrapped
```

Name	Size	Bytes	Class	Attributes
wrapped	1x7	112	py.list	

`wrapped` is a Python list, which is a list of Python strings. MATLAB shows this type as `py.list`.

Convert `py.list` to a cell array of Python strings.

```
wrapped = cell(wrapped);
```

```
whos wrapped
```

Name	Size	Bytes	Class	Attributes
wrapped	1x7	1568	cell	

Although `wrapped` is a MATLAB cell array, each cell element is a Python string.

```
wrapped{1}
```

```
ans =
```

```
Python str with no properties.
```

```
MATLAB(R) is a high-level language and interactive environment for
```

Convert the Python strings to MATLAB strings using the `char` function.

```
wrapped = cellfun(@char, wrapped, 'UniformOutput', false);
wrapped{1}
```

```
ans =
```

```
MATLAB(R) is a high-level language and interactive environment for
```

Now each cell element is a MATLAB string.

### Customize the Paragraph

Customize the output of the paragraph using keyword arguments.

The previous code uses the `wrap` convenience function, but the module provides many more options using the `py.textwrap.TextWrapper` functionality. To use the options, call `py.textwrap.TextWrapper` with keyword arguments described at <https://docs.python.org/2/library/textwrap.html#textwrap.TextWrapper>.

Create keyword arguments using the MATLAB `pyargs` function with a comma-separated list of name/value pairs. `width` formats the text to be 30 characters wide.

The `initial_indent` and `subsequent_indent` keywords begin each line with the comment character, `%`, used by MATLAB.

```
tw = py.textwrap.TextWrapper(pyargs(...
    'initial_indent', '% ', ...
    'subsequent_indent', '% ', ...
    'width', int32(30)));
wrapped = wrap(tw,T);
```

Convert to a MATLAB argument and display the results.

```
wrapped = cellfun(@char, cell(wrapped), 'UniformOutput', false);
fprintf('%s\n', wrapped{:})
```

```
% MATLAB(R) is a high-level
% language and interactive
% environment for numerical
% computation, visualization,
% and programming. Using
% MATLAB, you can analyze
% data, develop algorithms,
% and create models and
% applications. The language,
% tools, and built-in math
% functions enable you to
% explore multiple approaches
% and reach a solution faster
% than with spreadsheets or
% traditional programming
% languages, such as C/C++ or
% Java(TM).
```

## Use Beautiful Soup, a Third-Party Python Module

This example shows how to use a third-party module, Beautiful Soup, a tool for parsing HTML. If you want to run the example, you need to install this module using `apt-get`, `pip`, `easy_install`, or other tool you use to install Python modules.

First, find a Web page that includes a table of data. This example uses a table of the population of the world from the following English-language Wikipedia site. This example assumes the first table contains the population data, and assumes the country name is in the second column and the third column contains the population.

```
html = webread('http://en.wikipedia.org/wiki/List_of_countries_by_population');
```



```
soup = py.bs4.BeautifulSoup(html, 'html.parser');
```

Next, extract all of the table data from the HTML, creating a cell array. If you want a deeper understanding of what is happening, refer to the documentation for Beautiful Soup.

```
tables = soup.find_all('table');
t = cell(tables);
```

The first table is the one of interest; extract its rows.

```
c = cell(t{1}.find_all('tr'));
c = cell(c)';
```

Now loop over the cell array, extracting the country name and population from each row, found in the second and third columns respectively.

```
countries = cell(size(c));
populations = nan(size(c));

for i = 1:numel(c)
    row = c{i};
    row = cell(row.find_all('td'));
    if ~isempty(row)
        countries{i} = char(row{2}.get_text());
        populations(i) = str2double(char(row{3}.get_text()));
    end
end
```

Finally, create a MATLAB table from the data, and eliminate any lingering `nan` values; these NaNs represented invalid rows when importing the HTML.

```
data = table(countries, populations, ...
    'VariableNames', {'Country', 'Population'});
data = data(~isnan(data.Population), :);
```


Trim the tail end of the table and make a pie chart

```
restofWorldPopulation = sum(data.Population(11:end));
data = data(1:10, :);
data = [data; table({' Rest of World'}, restofWorldPopulation, ...
    'VariableNames', {'Country', 'Population'})]
pie(data.Population)
legend(data.Country, 'Location', 'EastOutside');
```

```
title('Distribution of World Population')
```

```
data =
```

Country	Population
'China[Note 2]'	1.3749e+09
'India'	1.2846e+09
'United States[Note 3]'	3.2287e+08
'Indonesia'	2.5871e+08
'Brazil'	2.0565e+08
'Pakistan'	1.9281e+08
'Nigeria'	1.8699e+08
'Bangladesh'	1.599e+08
'Russia[Note 4]'	1.4652e+08
'Japan'	1.2682e+08
' Rest of World'	3.0641e+09



### Learn More

It is sufficient to remember that Python is yet another potential source of libraries for the MATLAB user. If you want to learn about moving data between MATLAB and Python, including Python data types such as tuples and dictionaries, see “Call Python Libraries”.

## Call User-Defined Python Module

This example shows how to call methods from the following Python module. This module is used by examples in the documentation.

This example explains how to create the module in MATLAB. If you create `mymod.py` in a Python editor, be sure that the module is on the Python search path. This example also explains how to get help for calling the function, if you are not an experienced Python user.

Change your current folder to a writable folder.

Open a new file in MATLAB Editor.

Copy these commands and save the file as `mymod.py`.

```
# mymod.py
"""Python module demonstrates passing MATLAB types to Python functions"""
def search(words):
    """Return list of words containing 'son'"""
    newlist = [w for w in words if 'son' in w]
    return newlist

def theend(words):
    """Append 'The End' to list of words"""
    words.append('The End')
    return words
```

From the MATLAB command prompt, add the current folder to the Python search path.

```
if count(py.sys.path, '') == 0
    insert(py.sys.path, int32(0), '');
end
```

To learn how to call the function, read the function signature for the `search` function in the `mymod.py` source file. The function takes one input argument, `words`.

```
def search(words):
```

Read the function help in the `mymod.py` source file. According to the Python website documentation, help is in “a string literal that occurs as the first statement in a module, function, class, or method definition.” The help for `search` is:

```
"""Return list of words containing 'son'"""
```

The function returns a list.

Create an input argument, a list of names, in MATLAB.

```
N = py.list({'Jones', 'Johnson', 'James'})
```

```
N =
```

```
Python list with no properties.
```

```
['Jones', 'Johnson', 'James']
```

Call the `search` function. Type `py.` in front of the module name and function name.

```
names = py.mymod.search(N)
```

```
names =
```

```
Python list with no properties.
```

```
['Johnson']
```

The function returns a `py.list` value.

The original input, `N` is unchanged.

```
N
```

```
N =
```

```
Python list with no properties.
```

```
['Jones', 'Johnson', 'James']
```

## Related Examples

- “Reload Modified User-Defined Python Module” on page 1-50

## External Websites

- PEP 257 -- Docstring Conventions

## Use Python Numeric Types in MATLAB

This example shows how to use Python numbers in MATLAB. The trigonometry functions in the `math` module return Python `float` types. MATLAB automatically converts this type to `double`.

```
pynum = py.math.radians(90)
class(pynum)
```

```
pynum =
    1.5708
```

```
ans =
double
```

### More About

- “Pass Data to Python” on page 1-57

## Call Python Methods with Numeric Arguments

This example shows how to call the Python `math.fsum` function, which sums the floating-point values in an `iterable` input argument.

Open the MATLAB `patients.mat` sample data file and read the numeric array, `Height`.

```
load patients.mat
class(Height)
```

```
ans =
```

```
double
```

MATLAB automatically converts the numeric values to Python numeric values. However, `Height` is a 100-by-1 array, and MATLAB must pass a 1-by-N array to a Python `iterable` argument.

```
size(Height)
```

```
ans =
```

```
    100     1
```

Transform `Height` to a 1-by-N matrix before calling `fsum`.

```
py.math.fsum(Height')
```

```
ans =
```

```
    6707
```

### More About

- “Pass Data to Python” on page 1-57

## Default Numeric Types

By default, a number in MATLAB is a `double` type. By default, a number (without a fractional part) in Python is an integer type. This difference can cause confusion when passing numbers to Python functions.

For example, when you pass the following MATLAB numbers to the Python `datetime` function, Python reads them as `float` types.

```
d = py.datetime.date(2014,12,31)
```

```
Python Error: TypeError: integer argument expected, got float
```

Explicitly convert each number to an integer type:

```
d = py.datetime.date(int32(2014),int32(12),int32(31))
```

```
d =
```

```
Python date with properties:
```

```
    day: 31
  month: 12
   year: 2014
```

```
2014-12-31
```



## Use Python array Types in MATLAB

This example shows how to sum the elements of a Python `array.array` of type `double`.

Suppose that you have a Python function that returns the following array, `P`.

```
P =
```

```
Python array with properties:
```

```
    itemsize: 8  
    typecode: [1x1 py.str]  
  
array('d', [1.0, 2.0, 3.0, 4.0, 5.0])
```

Convert `P` to a MATLAB array of type `double`.

```
A = double(P);
```

Sum the elements of `A`.

```
sum(A)
```

```
ans =
```

```
    15
```

### More About

- “Unsupported MATLAB Types” on page 1-59

## Pass MATLAB Character Vector to Python Method

This example shows how to display the contents of a folder using the Python `os.listdir` method. The `listdir` method returns a list containing the names of the entries in the folder given by the path input argument.

Create a MATLAB variable representing a valid folder.

```
folder = fullfile(matlabroot, 'help', 'examples');
```

Pass `folder` to the `os.listdir` function. MATLAB automatically converts `folder` to the Python `str` type.

```
F = py.os.listdir(folder)
```

```
F =
```

```
Python list with no properties.
```

```
['graphics', 'graphics2', 'matlab']
```

MATLAB displays a list of folders, based on your product.

### More About

- “Pass Data to Python” on page 1-57

## Use Python str Type in MATLAB

This example shows how to use the Python path separator character (;).

```
p = py.os.path.pathsep
p =
    Python str with no properties.
    ;
```

In MATLAB, a Python character is a `py.str` variable.

MATLAB uses the same path separator character, ;.

```
c = pathsep
c =
    ;
```

Compare the MATLAB variable type to the Python type.

```
isequal(class(p),class(c))
ans =
    0
```

A `py.str` type is not equivalent to a MATLAB `char` type.

Convert `p` to a MATLAB type and append the character to a file name.

```
f = ['myfile' char(p)]
f =
    myfile;
```

### More About

- “Explicit Type Conversions” on page 1-60

## Pass MATLAB Backslash Control Character

This example shows how to pass the backslash control character (`\`) to a Python `str` type.

Insert the new line control character, `\n`, by calling the MATLAB `sprintf` function.

```
py.str(sprintf('The rain\nin Spain.'))
```

```
ans =
```

```
Python str with no properties.
```

```
The rain
in Spain.
```

Python replaces `\n` with a new line.

Without the `sprintf` function, both MATLAB and Python interpret `\` as a literal backslash.

```
py.str('The rain\nin Spain.')
```

```
ans =
```

```
Python str with no properties.
```

```
The rain\nin Spain.
```

Pass this string to a Python string method, `split`.

```
split(py.str('The rain\nin Spain.'))
```

```
ans =
```

```
Python list with no properties.
```

```
['The', 'rain\nin', 'Spain.']
```

Python treats the MATLAB character vector as a *raw string* and adds a `\` character to preserve the original backslash.

## Create Python list Variable

This example shows how to create a list variable to pass to a Python function.

```
students = py.list({'Robert', 'Mary', 'Joseph'})
```

```
students =
```

```
    Python list with no properties.
```

```
    ['Robert', 'Mary', 'Joseph']
```

Display number of students in the list.

```
n = py.len(students)
```

```
n =
```

```
    3
```

### More About

- “List, Tuple, and Dictionary Types” on page 1-67

## Use Python `list` Type in MATLAB

This example shows how to display folders on your system using the MATLAB `disp` function on the Python `sys.path` variable. `sys.path` is a `list` type.

Create a Python list, `P`, of folders on the Python search path.

```
P = py.sys.path;  
class(P)
```

```
ans =
```

```
py.list
```

Convert list `P` to a MATLAB type. The first step is to convert the list to a cell array of folder names, `cP`.

```
cP = cell(P);  
class(cP)
```

```
ans =
```

```
cell
```

Each folder name is a Python string.

```
class(cP{1})
```

```
ans =
```

```
py.str
```

Convert the Python strings in `cP` to MATLAB data using the `char` function. Put the values into a new cell array, `cellP`. Display the folder names.

```
cellP = cell(1, numel(cP));  
for n=1:numel(cP)  
    strP = char(cP{n});  
    cellP(n) = {strP};  
    disp(strP)  
end
```

```
C:\Python27\lib\site-packages\protobuf-2.5.0-py2.7.egg  
C:\windows\system32\python27.zip  
C:\Python27\DLLs
```

```
C:\Python27\lib
C:\Python27\lib\plat-win
C:\Python27\lib\lib-tk
C:\Python27
C:\Python27\lib\site-packages
```

MATLAB displays information specific to your Python installation.

Alternatively, create `cellP` using the `cellfun` function to combine the conversion functions.

```
cellP = cellfun(@char,cell(P), 'UniformOutput', false);
```

Display the folder names.

```
for n=1:py.len(P)
    disp(cellP{n})
end
```

## See Also

`cell` | `cellfun`

## More About

- “Handle Data Returned from Python” on page 1-60

## Use Python List of Numeric Types in MATLAB

This example shows how to convert a Python `list` of numeric values into a MATLAB array of double.

A Python list contains elements of any type and can contain elements of mixed types. The MATLAB `double` function used in this example assumes all elements of the Python list are numeric.

Suppose that you have a Python function that returns the following `list` of integers, `P`.

```
P =
```

```
Python list with no properties.
```

```
[1, 2, 3, 4]
```

Display the numeric type of the values.

```
class(P{1})
```

```
ans =
```

```
int64
```

Convert `P` to a MATLAB cell array.

```
cP = cell(P);
```

Convert the cell array to a MATLAB array of double.

```
A = cellfun(@double,cP)
```

```
A =
```

```
1 2 3 4
```

### See Also

[cell](#) | [cellfun](#)

### Related Examples

- “Use Python array Types in MATLAB” on page 1-15



## Pass Cell Array as Python Sequence Type

This example shows how to pass a MATLAB cell array to a Python function.

The following Python module contains the function `theend`, which appends text to the end of a list. Create a text file, copy this Python module, and save the file as `mymod.py` in a writable folder, for example, your `prefdir` folder.

```
# mymod.py
"""Python module demonstrates passing MATLAB types to Python functions"""
def search(words):
    """Return list of words containing 'son'"""
    newlist = [w for w in words if 'son' in w]
    return newlist

def theend(words):
    """Append 'The End' to list of words"""
    words.append('The End')
    return words
```

Add the folder containing `mymod.py` to the Python search path using the `append` method of the `list` type.

```
P = py.sys.path;
append(P,prefdir);
```

Open the MATLAB sample data file, creating the cell array, `LastName`.

```
load patients.mat
```

Convert the cell array to a 1-by-N `py.list` array.

```
L = py.list(LastName');
class(L)
```

```
ans =
```

```
py.list
```

Call `mymod.theend` on the list.

```
py.mymod.theend(L);
```

The Python function does not return variable `L` as an output argument. Instead, the function updates the value by reference.

View the last item in the list.

```
L{end}
```

```
ans =
```

```
Python str with no properties.  
The End
```

You can pass variable `L` to other Python functions.

## Related Examples

- “Use Python `list` Type in MATLAB” on page 1-20

## Read Element of Nested list Type

This example shows how to access an element of a Python list containing list elements.

```
matrix = py.list({{1, 2, 3, 4},{'hello','world'},{9, 10}});
```

Display element 'world', at index (2,2).

```
disp(char(matrix{2}{2}))
```

```
world
```

### More About

- “Multilevel Indexing to Access Parts of Cells”

## Use Python tuple Type in MATLAB

This example shows how to use a Python tuple, returned by the `os.path.split` function, in MATLAB.

```
pn = py.os.path.split('C:\Program Files\MATLAB\R2014a\help\examples')
```

```
pn =
```

```
Python tuple with no properties.
```

```
( 'C:\\Program Files\\MATLAB\\R2014a\\help', 'examples' )
```

Convert the parts of the folder to MATLAB variables and display the results.

```
head = char(pn{1})  
tail = char(pn{end})
```

```
head =
```

```
C:\Program Files\MATLAB\R2014a\help
```

```
tail =
```

```
examples
```

## Create Python tuple Variable

This example shows how to create a tuple variable to pass to a Python function.

```
student = py.tuple({'Robert', 19, 'Biology'})
```

```
student =
```

```
    Python tuple with no properties.
```

```
    ('Robert', 19.0, 'Biology')
```

### More About

- “List, Tuple, and Dictionary Types” on page 1-67

## Create Singleton Python tuple Variable

This example shows how to create a tuple variable with a single element.

```
subject = py.tuple({'Biology'})
```

```
subject =
```

```
    Python tuple with no properties.
```

```
    ('Biology',)
```

A tuple with one element has a trailing comma.

## Create Python dict Variable

This example shows how to create a `dict` variable to pass to a Python function.

```
studentID = py.dict(pyargs('Robert',357,'Mary',229,'Jack',391))
```

```
studentID =
```

```
    Python dict with no properties.
```

```
    {'Robert': 357.0, 'Jack': 391.0, 'Mary': 229.0}
```

### More About

- “List, Tuple, and Dictionary Types” on page 1-67

## Pass dict Argument to Python Method

This example shows how to change a value in a `dict` variable using the Python update method.

Create a menu of items and prices.

```
menu = py.dict(pyargs('soup',3.57,'bread',2.29,'bacon',3.91,'salad',5.00));
```

Update the price for bread using the Python `dict` type update method.

```
update(menu,py.dict(pyargs('bread',2.50)))  
menu
```

```
menu =
```

```
Python dict with no properties.
```

```
{'soup': 3.57, 'bacon': 3.91, 'bread': 2.5, 'salad': 5.0}
```



## Use Python dict Type in MATLAB

This example shows how to convert numerical values of a Python dict variable into a MATLAB array.

Suppose that you have a Python function, `myfunc`, that returns menu items and prices in a dictionary, `dict`, type.

```
order = myfunc;
```

```
order =
```

```
Python dict with no properties.
```

```
{'soup': 3.57, 'bacon': 3.91, 'salad': 5.0, 'bread': 2.29}
```

A dictionary has pairs of keys and values. Use the Python `keys` function to display the menu items.

```
keys(order)
```

```
ans =
```

```
Python list with no properties.
```

```
['soup', 'bacon', 'salad', 'bread']
```

Use the Python `values` function to display the prices.

```
values(order)
```

```
ans =
```

```
Python list with no properties.
```

```
[3.57, 3.91, 5.0, 2.29]
```

Use the `cell` function to convert the Python list to a MATLAB variable.

```
p = cell(values(order))
```

```
p =
```

```
[3.5700] [3.9100] [5] [2.2900]
```

Convert the prices to a MATLAB array.

```
prices = cellfun(@double,p)
```

```
prices =
```

```
        3.57        3.91        5.00        2.29
```

Calculate the total.

```
total = sum(prices)
```

```
total =
```

```
    14.77
```

## Convert Python dict Type to MATLAB Structure

This example shows how to plot numeric data from a Python dictionary.

Suppose a Python function returns a variable, `patient`, with the following values.

```
patient
```

```
patient =
```

```
Python dict with no properties.
```

```
{'test1': array('d', [79.0, 75.0, 73.0]),  
 'test3': array('d', [220.0, 210.0, 205.0]),  
 'test2': array('d', [180.0, 178.0, 177.5]),  
 'name': 'John Doe'}
```

Convert `patient` to a MATLAB structure.

```
P = struct(patient)
```

```
P =
```

```
test1: [1x1 py.array.array]  
test3: [1x1 py.array.array]  
test2: [1x1 py.array.array]  
name: [1x8 py.str]
```

The values of the fields remain as Python types.

Plot the test results after converting the numeric data to type double.

```
bar([double(P.test1);double(P.test2);double(P.test3)])
```

MATLAB displays a bar graph.

## Pass Keyword Arguments

The Python built-in `print` function has keyword arguments, `sep`, `end`, and `file`.

```
print(*objects, sep=' ', end='\n', file=sys.stdout)
```

The following examples use the default value for `file`.

Create some text variables.

```
x1 = py.str('c:');  
x2 = py.os.curdir;  
x3 = py.os.getenv('foo');  
py.print(x1,x2,x3)
```

```
c: . None
```

To display the values on separate lines, use newline, `\n`, as a separator.

```
py.print(x1,x2,x3,pyargs('sep',sprintf('\n')))
```

```
c:  
.  
None
```

Use the following statement to change `sep` to an empty string and change the `end` value to display `THE END`.

```
py.print(x1,x2,x3,pyargs('end', sprintf(' THE END\n'),'sep',py.str))
```

```
c: .None THE END
```

### See Also

`pyargs`

### External Websites

- [python.org](https://python.org) `print` function

## Pass Python Function to Python map Function

This example shows how to display the length of each word in a list.

Create a list of days of the work week.

```
days = py.list({'Monday', 'Tuesday', 'Wednesday', 'Thursday', 'Friday'});
```

Apply the Python `len` function to the `py.map` function to display the length of each word. Use the MATLAB function handle notation, `@`, to indicate `py.len` is a function.

```
py.map(@py.len, days)
```

```
ans =
```

```
Python list with no properties.
```

```
[6, 7, 9, 8, 6]
```

Python version 2.7 returns a list.

Python versions 3.x return a `map` object. To display the contents, type:

```
py.list(py.map(@py.len, days))
```

```
ans =
```

```
Python list with no properties.
```

```
[6, 7, 9, 8, 6]
```

### External Websites

- [python.org](http://python.org) map function

## Index into Python String

This example shows how to display the first character of a Python `str` variable. The example compares indexing into a MATLAB character vector with indexing into the Python variable.

Create a MATLAB character vector and display the first character.

```
str = 'myfile';  
str(1)
```

```
ans =
```

```
m
```

Convert the character vector to a Python `str` type and display the first character.

```
pstr = py.str(str);  
pstr(1)
```

```
ans =
```

```
Python str with no properties.
```

```
m
```

## Index into Python List

This example shows how to display the last element in a Python `list` variable. The example compares indexing into a MATLAB cell array with indexing into a Python list.

Create a MATLAB cell array and display the last element.

```
C = {1,2,3,4};  
n = C(end)  
  
n =
```

```
[4]
```

MATLAB returns a cell array.

Display the contents of the last element.

```
n = C{end}  
  
n =
```

```
4
```

Convert the cell array to a Python list.

```
li = py.list(C)  
  
li =
```

```
Python list with no properties.
```

```
[1.0, 2.0, 3.0, 4.0]
```

Display the last element.

```
n = li(end)  
  
n =
```

```
Python list with no properties.
```

```
[4.0]
```

MATLAB returns a list.

Display the contents of the last element.

```
n = li{end}
```

```
n =
```

```
4
```



## Index into Python Tuple

This example shows how to display elements in a tuple.

Create a tuple and display the first two elements.

```
t = py.tuple({'a', 'bc', 1, 2, 'def'});  
t(1:2)
```

```
ans =
```

```
Python tuple with no properties.
```

```
('a', 'bc')
```

MATLAB returns a tuple.

## Index into Python dict

This example shows how to display an element in a dictionary.

Create a dictionary variable.

```
customers = py.dict
customers =
    Python dict with no properties.
    {}
```

Populate the dict with customer names and account numbers.

```
customers{'Smith'} = int32(2112);
customers{'Anderson'} = int32(3010);
customers{'Audrey'} = int32(4444);
customers{'Megan'} = int32(5000);

customers =
    Python dict with no properties.
    {'Audrey': 4444, 'Anderson': 3010, 'Smith': 2112, 'Megan': 5000}
```

The output depends on your Python version.

Read the account number for customer Anderson.

```
acct = customers{'Anderson'}
acct =
    3010
```

The result is a double.

```
class(acct)
ans =
double
```

## Use Python List as Values in for Loop

This example shows how to display elements of a Python list.

```
li = py.list({1,2,3,4});  
for n = li  
    disp(n{1})  
end
```

1

2

3

4

Variable `n` is a `py.list` with one element.

### More About

- “Access Elements in Python Container Types” on page 1-43

## Display Stepped Range of Elements

This example shows how to use an incremental step in indexing.

If you use slicing to access elements of a Python object, the format in Python is `start:stop:step`. In MATLAB, the syntax is of the form `start:step:stop`.

```
li = py.list({'a', 'bc', 1, 2, 'def'});  
li(1:2:end)
```

```
ans =
```

```
Python list with no properties.
```

```
['a', 1.0, 'def']
```

## Access Elements in Python Container Types

### In this section...

“Sequence Types” on page 1-43

“Mapping Types” on page 1-44

“Size and Dimensions” on page 1-44

“Array Support” on page 1-45

“Use Zero-Based Indexing for Python Functions” on page 1-45

Typically, to work with a Python variable in MATLAB, you convert the Python object to a MATLAB array, and then index into the array as needed. Sometimes, you want to preserve the Python object.

A Python *container* is typically a *sequence* type (list or tuple) or a *mapping* type (dict). In Python, use square brackets [ ] or the operator `.getitem` function to access an element in the container.

### Sequence Types

Python sequence types behave like MATLAB cell arrays.

Get a subsequence using smooth-parenthesis ( ) indexing.

```
li = py.list({1,2,3,4});
res = li(2:3)
```

```
res =
```

```
    Python list with no properties.
```

```
    [2.0, 3.0]
```

Use curly braces { } to get the contents of the element.

```
res = li{1}
```

```
res =
```

```
    1
```

## Mapping Types

For mapping types, use curly braces with the Python *key* argument.

```
patient = py.dict(pyargs('name', 'John Doe', 'billing', 127));  
patient{'billing'}
```

```
ans =
```

```
127
```

## Size and Dimensions

MATLAB displays information for your system.

```
p = py.sys.path;  
class(p)
```

```
ans =
```

```
py.list
```

Index into p.

```
p(1)  
p{1}
```

```
ans =
```

```
Python list with no properties.
```

```
['c:\\work']
```

```
ans =
```

```
Python str with no properties.
```

```
c:\work
```

Inspect dimensions.

```
len = length(p)  
sz = size(p)
```

```
len =  
    11  
  
sz =  
    1    11
```

## Array Support

MATLAB converts a sequence type into a 1-by-N array.

## Use Zero-Based Indexing for Python Functions

Python uses zero-based indexing; MATLAB uses one-based indexing. When you call a Python function, such as `py.sys.path`, the index value of the first element of a Python container, `x`, is `int32(0)`. The index value for the last element is `int32(py.len(x) - 1)`.

## Related Examples

- “Index into Python String” on page 1-36
- “Index into Python List” on page 1-37
- “Index into Python Tuple” on page 1-39
- “Index into Python `dict`” on page 1-40

## More About

- “Explicit Type Conversions” on page 1-60
- “Limitations to Indexing into Python Objects” on page 1-69
- “Pass MATLAB Backslash Control Character” on page 1-18

## View Python Numeric Values

<b>In this section...</b>
“Why Do I See Properties When I Display a Number?” on page 1-46
“What Is the L Character Attached to a Number?” on page 1-46

### Why Do I See Properties When I Display a Number?

MATLAB displays all Python types as objects, including a list of properties of the object.

```
py.int(5)
```

```
ans =
```

```
Python int with properties:
```

```
denominator: 1
             imag: 0
             numerator: 5
             real: 5
```

```
5
```

MATLAB displays the expected output value (5) on the last line.

### What Is the L Character Attached to a Number?

Python appends an L character to the representation (display) of a long data type. For example, using Python version 2.7, type:

```
py.repr(py.long(5))
```

```
ans =
```

```
Python str with no properties.
```

```
5L
```

MATLAB displays Python `str` and appends L for any Python function that uses the `repr` function to display its output.



You treat a `long` data type like any numeric type. For example, add two numbers:

```
py.long(5) + py.long(2)
```

```
ans =
```

```
Python long with properties:
```

```
denominator: [1x1 py.long]  
  imag: [1x1 py.long]  
numerator: [1x1 py.long]  
  real: [1x1 py.long]
```

```
7
```

The answer is the number 7.

## Call Methods on Python Variables

This example shows how to update a Python `list` of folder names using the `append` method.

Create a `list` of folders, `P`, using the Python `sys.path` variable.

```
P = py.sys.path;
```

Display the Python functions for a `list` type.

```
methods(P)
```

```
Methods for class py.list:
```

```
append  count  display  ge      insert  lt      plus     reverse
cell    details eq      gt      le      mtimes  pop      sort
char    disp   extend  index  list    ne      remove
```

```
Methods of py.list inherited from handle.
```

Read the documentation for `append`.

```
py.help('list.append')
```

```
Help on method_descriptor in list:
```

```
list.append = append(...)
    L.append(object) -- append object to end
```

Add the current folder to the end of the path.

```
append(P, pwd)
```

Display number of folders on the path. The list has `py.len` elements.

```
py.len(P)
```

```
ans =
```

```
Python int with properties:
```

```
    real: [1x1 py.int]
denominator: [1x1 py.int]
    imag: [1x1 py.int]
```

```
numerator: [1x1 py.int]
```

```
11
```

11 is the number of folders on this path. Your value might be different. The type of this number is `py.int`.

## Related Examples

- “Use Python `list` Type in MATLAB” on page 1-20

## Reload Modified User-Defined Python Module

This example shows how to reload a modified Python module.

When you use this workflow, MATLAB deletes all variables, scripts, and classes in the workspace. For more information, see the `clear classes` function.

The Python calling syntax to reload the module depends on your Python version. To verify your Python version, use the MATLAB `pyversion` function.

### Create Python Module

Change your current folder to a writable folder. Open a new file in MATLAB Editor.

Copy these statements defining a `myfunc` function and save the file as `mymod.py`.

```
def myfunc():  
    """Display message."""  
    return 'version 1'
```

Call `myfunc`.

```
py.mymod.myfunc
```

```
ans =
```

```
Python str with no properties.
```

```
version 1
```

### Modify Module

Modify the function, replacing the `return` statement with the following:

```
return 'version 2'
```

Save the file.

### Unload Module

```
clear classes
```

MATLAB deletes all variables, scripts, and classes in the workspace.

**Import Modified Module**

```
mod = py.importlib.import_module('mymod');
```

**Reload Module in Python Version 2.7**

```
py.reload(mod);
```

**Reload Module in Python Version 3.3**

```
py.imp.reload(mod);
```

**Reload Module in Python Versions 3.4 and 3.5**

```
py.importlib.reload(mod);
```

**Call Function in Updated Module**

Call the updated myfunc function.

```
py.mymod.myfunc
```

```
ans =
```

```
    Python str with no properties.
```

```
    version 2
```

**See Also**

`clear` | `pyversion`

**Related Examples**

- “Call User-Defined Python Module” on page 1-10

## System and Configuration Requirements

In this section...
“Python Version Support” on page 1-52
“Set Python Version on Windows Platform” on page 1-52
“Set Python Version on Mac and Linux Platforms” on page 1-53
“Download 64-bit Version of Python on Windows Platforms” on page 1-53
“Requirements for Building Python Executable” on page 1-53

### Python Version Support

To call Python modules in MATLAB you must have a supported version of the reference implementation (CPython) installed on your system. MATLAB supports the following versions:

- Version 2.7
- Version 3.3
- Version 3.4
- Version 3.5

To determine if your system has a supported version, use the `pyversion` function. The value set by `pyversion` is persistent across MATLAB sessions.

You cannot switch between versions of Python in a single MATLAB session. MATLAB automatically selects and loads a Python version when you type a Python command, such as:

```
py.funcname
```

If you want to change versions, restart MATLAB and then run `pyversion` with the new version information.

### Set Python Version on Windows Platform

On Windows platforms, use either:

```
pyversion version
```

or

```
pyversion executable
```

---

**Note:** If you downloaded a Python interpreter, but did not register it in the Windows registry, use:

```
pyversion executable
```

---

## Set Python Version on Mac and Linux Platforms

To set the version, type:

```
pyversion executable
```

where *executable* is the full path to the Python executable file.

## Download 64-bit Version of Python on Windows Platforms

The architecture of Python must match the architecture of MATLAB. On the Python download website, downloads for Microsoft Windows platforms are 32-bit versions by default. To download the 64-bit version, choose options with the name "Windows x86-64 MSI installer".

---

**Note:**

---

## Requirements for Building Python Executable

On Linux<sup>®</sup> and Mac systems, if you build the Python executable, configure the build with the `--enable-shared` option.

### See Also

`pyversion`

## External Websites

- <https://www.python.org/downloads>

## Create a Python Object

The syntax to create a Python object `pyObj` is:

```
pyObj = py.modulename.ClassName(varargin)
```

where `varargin` is the list of constructor arguments specified by the `__init__` method in `ClassName`.

In MATLAB, Python objects are *reference types* (handle objects) and do not adhere to the MATLAB copy-on-assignment and pass-by-value rules. When you copy a handle object, only the handle is copied and both the old and new handles refer to the same data. When you copy a MATLAB variable (a value object), the variable data is also copied. The new variable is independent of changes to the original variable.

The following example creates an object of the `TextWrapper` class in the Python standard library `textwrap` module.

Read the constructor signature, `__init__`.

```
py.help('textwrap.TextWrapper.__init__')
```

```
Help on method __init__ in textwrap.TextWrapper:
```

```
textwrap.TextWrapper.__init__ = __init__(self, width=70, initial_indent='', subsequent_
```

Create a default `TextWrapper` object. You do not need to pass any input arguments because each argument has a default value, identified by the equal sign (=) character.

```
tw = py.textwrap.TextWrapper;
```

```
tw =
```

Python `TextWrapper` with properties:

```
          width: 70
    subsequent_indent: [1x1 py.str]
wordsep_simple_re_uni: [1x1 py._sre.SRE_Pattern]
    fix_sentence_endings: 0
      break_on_hyphens: 1
    break_long_words: 1
      wordsep_re_uni: [1x1 py._sre.SRE_Pattern]
      initial_indent: [1x1 py.str]
      expand_tabs: 1
```



```

replace_whitespace: 1
drop_whitespace: 1

```

```
<textwrap.TextWrapper instance at 0x000000006D58F808>
```

To change a logical value, for example, the `break_long_words` property, type:

```
tw.break_long_words = 0;
```

To change a numeric value, for example, the `width` property, first determine the numeric type.

```
class(tw.width)
```

```
ans =
```

```
int64
```

By default, when you pass a MATLAB number to a Python function, Python reads it as a float. If the function expects an integer, Python might throw an error or produce unexpected results. Explicitly convert the MATLAB number to an integer. For example, type:

```
tw.width = int64(3);
```

Read the help for the `wrap` method.

```
py.help('textwrap.TextWrapper.wrap')
```

```
Help on method wrap in textwrap.TextWrapper:
```

```
textwrap.TextWrapper.wrap = wrap(self, text) unbound textwrap.TextWrapper method
wrap(text : string) -> [string]
```

```

Reformat the single paragraph in 'text' so it fits in lines of
no more than 'self.width' columns, and return a list of wrapped
lines. Tabs in 'text' are expanded with string.expandtabs(),
and all other whitespace characters (including newline) are
converted to space.

```

Create a list of wrapped lines, `w`, from input `T`.

```

T = 'MATLAB® is a high-level language and interactive environment for numerical comput
w = wrap(tw,T);
whos w

```

Name	Size	Bytes	Class	Attributes
w	1x1	112	py.list	

Convert the `py.list` to a cell array and display the results.

```
wrapped = cellfun(@char, cell(w), 'UniformOutput', false);  
fprintf('%s\n', wrapped{:})
```

```
MATLAB®  
is  
a  
high-  
level  
language  
and  
interactive  
environment  
for  
numerical  
computation,  
visualization,  
and  
programming.
```

Although `width` is 3, setting the `break_long_words` property to `false` overrides the `width` value in the display.

## Related Examples

- “Call Python from MATLAB” on page 1-4
- “Pass Keyword Arguments” on page 1-34

## More About

- “Why Use Object-Oriented Design”

## Pass Data to Python

### In this section...

“MATLAB Type to Python Type Mapping” on page 1-57

“MATLAB Vector to Python Mapping” on page 1-58

### MATLAB Type to Python Type Mapping

When you pass MATLAB data as arguments to Python, MATLAB converts the data into types that best represent the data to the Python language.

MATLAB Input Argument Type — Scalar Values Only	Resulting Python Type
double single	float
Complex single Complex double	complex
int8 uint8 int16 uint16 int32	int
uint32 int64 uint64	int long (version 2.7 only)
NaN	float(nan)
Inf	float(inf)
logical	bool
Structure	dict
Python object — <i>py.type</i>	<i>type</i>
function handle <i>@py.module.function</i> , to Python functions only	<i>module.function</i>

## MATLAB Vector to Python Mapping

MATLAB Input Argument Type — 1-by-N Vector	Resulting Python Type
double	<code>array.array('d')</code>
single	<code>array.array('f')</code>
int8	<code>array.array('b')</code>
uint8	<code>array.array('B')</code>
int16	<code>array.array('h')</code>
uint16	<code>array.array('H')</code>
int32	<code>array.array('i')</code>
uint32	<code>array.array('I')</code>
int64 (Not supported for Python 2.7 on Windows)	<code>array.array('q')</code>
uint64 (Not supported for Python 2.7 on Windows)	<code>array.array('Q')</code>
char array containing values greater than <code>intmax('uint8')</code> (version 2.7 only)	unicode
char array	str
cell vector	tuple

### Related Examples

- “Pass dict Argument to Python Method” on page 1-30

### More About

- “Handle Data Returned from Python” on page 1-60
- “Unsupported MATLAB Types” on page 1-59

## Unsupported MATLAB Types

The following MATLAB types are not supported in Python.

Unsupported MATLAB Types
Multidimensional arrays (numeric, char, or cell)
Structure arrays
Complex, scalar integers or arrays
Sparse arrays
Logical vectors
categorical, table, containers.Map, datetime types
MATLAB objects
meta.class (py.class)

### More About

- “Pass Data to Python” on page 1-57

## Handle Data Returned from Python

**In this section...**

“Automatic Python Type to MATLAB Type Mapping” on page 1-60

“Explicit Type Conversions” on page 1-60

### Automatic Python Type to MATLAB Type Mapping

The following table shows how MATLAB converts data returned from Python into MATLAB types.

Python Return Type, as Displayed in Python	Resulting MATLAB Type — Scalar
<code>bool</code>	<code>logical</code>
<code>int</code> (version 2.7 only). For Python versions 3.x <code>int</code> , you must convert explicitly.	<code>int64</code>
<code>float</code>	<code>double</code>
<code>complex</code>	Complex <code>double</code>
All other Python types — <code>type</code>	Python object — <code>py.type</code>

### Explicit Type Conversions

MATLAB provides the following functions to convert Python data types to MATLAB types manually.

Python Return Type or Protocol, as Displayed in MATLAB	MATLAB Conversion Function
<code>py.str</code> (version 2.7)	<code>char</code> <code>uint8</code>
<code>py.str</code> (version 3.x)	<code>char</code>
<code>py.unicode</code>	<code>char</code>
Object with <code>__str__</code> method	<code>char</code>
<code>py.bytes</code>	<code>uint8</code>

Python Return Type or Protocol, as Displayed in MATLAB	MATLAB Conversion Function
<code>py.int</code>	double or int64
<code>py.long</code>	double or int64
<code>py.array.array<sup>a</sup></code>	numeric double single int8 uint8 int16 uint16 int32 uint32 int64 uint64
Sequence protocol; for example, <code>py.list</code> and <code>py.tuple</code>	cell
Mapping protocol; for example, <code>py.dict</code>	struct

a. You can convert `py.array.array` of any format to the MATLAB type you want.

## More About

- “Pass Data to Python” on page 1-57

## How MATLAB Represents Python Operators

MATLAB supports the following overloaded operators.

Python Operator Symbol	Python Methods	MATLAB Methods
+ (binary)	<code>__add__</code> , <code>__radd__</code>	plus, +
- (binary)	<code>__sub__</code> , <code>__rsub__</code>	minus, -
* (binary)	<code>__mul__</code> , <code>__rmul__</code>	mtimes, *
/	<code>__truediv__</code> , <code>__rtruediv__</code>	mrdivide, /
==	<code>__eq__</code>	eq, ==
>	<code>__gt__</code>	gt, >
<	<code>__lt__</code>	lt, <
!=	<code>__ne__</code>	ne, ~=
>=	<code>__ge__</code>	ge, >=
<=	<code>__le__</code>	le, <=
- (unary)	<code>__neg__</code>	uminus, -a
+ (unary)	<code>__pos__</code>	uplus, +a

The following Python operators are not supported.

Python Operator Symbol	Python Method
%	<code>__mod__</code> , <code>__rmod__</code>
**	<code>__pow__</code> , <code>__rpow__</code>
<<	<code>__lshift__</code> , <code>__rlshift__</code>
>>	<code>__rshift__</code> , <code>__rrshift__</code>
&	<code>__and__</code> , <code>__rand__</code>
^	<code>__xor__</code> , <code>__rxor__</code>
	<code>__or__</code> , <code>__ror__</code>
// (binary)	<code>__floordiv__</code> , <code>__rfloordiv__</code>
+= (unary)	<code>__iadd__</code>



Python Operator Symbol	Python Method
<code>-=</code> (unary)	<code>__isub__</code>
<code>*=</code> (unary)	<code>__imul__</code>
<code>/=</code> (unary)	<code>__itruediv__</code>
<code>//=</code> (unary)	<code>__ifloordiv__</code>
<code>%=</code> (unary)	<code>__imod__</code>
<code>**=</code> (unary)	<code>__ipow__</code>
<code>&lt;&lt;=</code> (unary)	<code>__ilshift__</code>
<code>&gt;&gt;=</code> (unary)	<code>__irshift__</code>
<code>&amp;=</code> (unary)	<code>__iand__</code>
<code>^=</code> (unary)	<code>__ixor__</code>
<code>!=</code> (unary)	<code>__ior__</code>
<code>~</code> (unary)	<code>__invert__</code>

## Execute Callable Python Object

To execute a callable Python object, use the `feval` function. For example, if instance *obj* of a Python class is callable, replace the Python syntax `obj(x1, ..., xn)` with one of the following MATLAB statement:

```
feval(obj,x1, ..., xn)
```

```
obj(x1, ..., xn)
```

### See Also

`feval`

## Python import and MATLAB import Commands

### In this section...

“Do Not Type “import *pythonmodule*”” on page 1-65

“Use MATLAB import to Shorten Class or Function Names” on page 1-65

### Do Not Type “import *pythonmodule*”

MATLAB automatically loads Python when you type:

```
py.command
```

Do not type “import *pythonmodule*” in MATLAB.

The `import` statement does not have the same functionality in MATLAB as in Python. Python uses the `import` statement to load and make code accessible. MATLAB uses the `import` function to refer to a class or function without using the package name.

### Use MATLAB `import` to Shorten Class or Function Names

The Python `from...import` statement lets you reference a module without using the fully qualified name. Replace the following Python statement:

```
from x import y
```

with the MATLAB command

```
import x.y
```

where `y` is a class name or function name you want to use.

For example, the Python `textwrap` module formats blocks of text.

```
S = py.textwrap.wrap('This is a string');
```

Since `wrap` is not a MATLAB function, you can shorten the calling syntax using the `import` function. After calling this command, you do not need to type the package (`py`) and module (`textwrap`) names.

```
import py.textwrap.wrap
```

```
S = wrap('This is a string');
```

---

**Note:** Do not call:

```
import py.*
```

If you do, MATLAB calls the Python function instead of the MATLAB function of the same name.

If you call this command, you must call the MATLAB command:

```
clear import
```

---

## See Also

import

## List, Tuple, and Dictionary Types

The following table shows the commands for creating `list`, `tuple`, and `dict` types. The commands on the left are run from the Python interpreter. The commands on the right are MATLAB commands.

Python <code>list</code> – <code>[]</code>	MATLAB <code>py.list</code>
<code>['Robert', 'Mary', 'Joseph']</code>	<code>py.list({'Robert', 'Mary', 'Joseph'})</code>
<code>[[1,2],[3,4]]</code>	<code>py.list({py.list([1,2]),py.list([3,4])})</code>
Python <code>tuple</code> – <code>()</code>	MATLAB <code>py.tuple</code>
<code>('Robert', 19, 'Biology')</code>	<code>py.tuple({'Robert',19,'Biology'})</code>
Python <code>dict</code> – <code>{}</code>	MATLAB <code>py.dict</code>
<code>{'Robert': 357, 'Joe': 391, 'Mary': 229}</code>	<code>py.dict(pyargs(... 'Robert',357,'Mary',229,'Joe',391))</code>

### See Also

`pyargs`

### Related Examples

- “Use Python `list` Type in MATLAB” on page 1-20
- “Use Python `tuple` Type in MATLAB” on page 1-26
- “Use Python `dict` Type in MATLAB” on page 1-31

## Limitations to Python Support

Features Not Supported in MATLAB
Closing the Python interpreter while running MATLAB.
Saving (serializing) Python objects into a MAT-file.
Interactive Python help (calling <code>py.help</code> without input arguments).
<code>py.input</code> and <code>py.raw_input</code> (version 2.7).
Accessing static properties of a Python class.
MATLAB <code>isa</code> function does not recognize virtual inheritance.
MATLAB class inheritance from a Python class.
Customized (dynamic) attribute access.
Nested Python classes.
Modules that start MATLAB in a separate process, for example, the <code>multiprocessing</code> module.
Modules that read <code>sys.argv</code> , the command-line arguments passed to a Python script, for example, <code>Tkinter</code> .
Dynamically generated Python classes, for example, <code>collections.namedtuple</code> .
Dynamically attaching new object attributes. Instead, use <code>py setattr</code> .
Class names or other identifiers starting with an underscore ( <code>_</code> ) character. Instead, use the Python <code>py.getattr</code> and <code>py setattr</code> functions.
Python modules generated by the MATLAB Compiler SDK™ product.
Python code using Cocoa (AppKit) for user interfaces on Mac OS X platforms.

### More About

- “Python `import` and MATLAB `import` Commands” on page 1-65
- “Unsupported MATLAB Types” on page 1-59

## Limitations to Indexing into Python Objects

You can access data in Python container objects, like lists and dictionaries, with index values, similar to referencing an element in a MATLAB matrix. There are, however, ways to index into matrices which are not supported for these Python types.

Indexing Features Not Supported in MATLAB
Use of square brackets, [ ].
Indexing into a container type that does not inherit from <code>collections.Sequence</code> or <code>collections.Mapping</code> .
Logical indexing.
Accessing data in a container with an arbitrary array of indices. An index must be of the form <code>start:step:stop</code> .
Comma-separated lists.
<code>numel</code> function does not return number of array elements. Returns 1.

### More About

- “Matrix Indexing”

## Undefined variable "py" or function "py.command"

MATLAB automatically loads Python when you type `py.command` in the Command Window. If MATLAB displays this message, a failure has occurred.

```
Undefined variable "py" or function "py.command"
```

Use this page to help troubleshoot the failure.

### In this section...

"Python Not Installed" on page 1-70

"64-bit/32-bit Versions of Python on Windows Platforms" on page 1-70

"MATLAB Cannot Find Python" on page 1-70

"Error in User-Defined Python Module" on page 1-71

"Python Module Not on Python Search Path" on page 1-71

"Module Name Conflicts" on page 1-72

"Python Tries to Execute command in Wrong Module" on page 1-72

## Python Not Installed

Python is not installed on your computer. Download and install Python from <https://www.python.org/downloads>.

On Microsoft Windows, Python downloads the 32-bit version of Python by default. If you run a 64-bit version of MATLAB, download a 64-bit version of Python, identified by the name "Windows x86-64 MSI installer". For more information, see "Download 64-bit Version of Python on Windows Platforms" on page 1-53.

On Linux and Mac systems, if you build Python from source files, configure the build with the `--enable-shared` option.

## 64-bit/32-bit Versions of Python on Windows Platforms

You installed a 32-bit version of Python for a 64-bit version of MATLAB.

## MATLAB Cannot Find Python

Python is in a nonstandard location. To provide the path to the Python executable, use the `pyversion` function. For example:



```
pyversion C:\Users\uname\WinPython-64bit-3.3.2.1\python-3.3.2.amd64\python.exe
```

On Windows systems, Python is not found in the Windows registry. If you downloaded a Python interpreter, but did not register it in the Windows registry, specify the Python location using the command:

```
pyversion executable
```

## Error in User-Defined Python Module

There is an error in the user-defined Python module. To test if your module, *mymod*, contains errors, type:

```
py.importlib.import_module('mymod')
```

If Python detects an error in the module, MATLAB displays a Python error message.

Alternatively, execute the equivalent command at the Python command prompt to get the Python error message.

After you fix the error, to access the updated module, restart MATLAB, and add it to the search path.

## Python Module Not on Python Search Path

If *command* is a valid Python command, make sure the Python module is on the Python search path. To test if module *mymod* is on the path, type:

```
py.importlib.import_module('mymod')
```

If Python cannot find the module, MATLAB displays a Python error message.

To add *mymod*, in folder *modpath*, to the path, type:

```
P = py.sys.path;  
if count(P,'modpath') == 0  
    insert(P,int32(0),'modpath');  
end
```

The Python search path is associated with the Python interpreter loaded in the current session of MATLAB. You can modify the search path in MATLAB, but the modifications are not present if you run other instances of the interpreter outside of MATLAB.

## Module Name Conflicts

If you call a Python module that has the same name as a module in the standard library or any 3rd-party modules installed on your system, MATLAB might load the wrong module.

## Python Tries to Execute *command* in Wrong Module

If *command* is in a user-defined module, make sure that the module name does not conflict with modules in the Python standard library, or any 3rd-party modules on your system.

## See Also

pyversion

## More About

- “System and Configuration Requirements” on page 1-52

## External Websites

- <https://www.python.org/downloads>

## Help for Python Functions

For a complete description of Python functionality, consult outside resources, in particular, `python.org`. There are different versions of the Python documentation, so be sure to refer to the version corresponding to the version on your system. Many examples in the MATLAB documentation refer to functions in the Python standard library.

To use functions in a third-party or user-defined Python module, refer to your vendor product documentation for information about how to install the module and for details about its functionality.

The `py.help` command displays the Python help found at `www.python.org/doc`. Help for packages and classes can be extensive and might not be useful when displayed in the MATLAB command window.

- Package  
`py.help('textwrap')`
- Class  
`py.help('textwrap.TextWrapper')`
- Method of a class  
`py.help('textwrap.TextWrapper.wrap')`
- Function  
`py.help('textwrap.fill')`

If MATLAB displays an error message beginning with `Python Error:`, refer to your Python documentation for more information.

---

**Note:** You cannot use the interactive Python help, calling `py.help` without input arguments, in MATLAB.

---

### More About

- “Handle Python Exceptions” on page 1-74

### External Websites

- `www.python.org`

## Handle Python Exceptions

MATLAB catches exceptions thrown by Python and converts them into a `matlab.exception.PyException` object, which is derived from the `MException` class. For example:

```
try
    py.list('x','y',1)
catch e
    e.message
    if(isa(e,'matlab.exception.PyException'))
        e.ExceptionObject
    end
end
```

```
ans =
```

```
Python Error: TypeError: list() takes at most 1 argument (3 given)
```

```
ans =
```

```
Python tuple with no properties.
```

```
(<type 'exceptions.TypeError'>, TypeError('list() takes at most 1 argument (3 given
```

If MATLAB displays an error message of the following format, refer to your Python documentation for more information.

```
Python Error: Python class: message
```

### See Also

`matlab.exception.PyException`

## Troubleshooting Error Messages

Troubleshooting errors when using a MATLAB external interface is a challenge. Is the error in the Python application or in your MATLAB code? Common errors include errors reported by Python and errors from attempting to convert Python data to MATLAB and conversely.

### In this section...

“Python Error: Python class: message” on page 1-75

“Python Module Errors” on page 1-75

“Errors Converting Python Data” on page 1-76

### Python Error: *Python class: message*

MATLAB displays an error message in the following format:

```
Python Error: Python class: message
```

MATLAB displays *message* only if there is a Python error message.

This error comes from Python and for information you must refer to your version of Python documentation at [www.python.org/doc](http://www.python.org/doc) or the product documentation from third-party vendors. For example:

```
p = py.os.path.split(pwd);  
py.operator.setitem(p,int32(1),py.str('temp'));
```

```
Python Error: TypeError: 'tuple' object does not support item assignment
```

Search for the term “tuple” on the Python documentation site for your version of Python. Tuple is a built-in function described here: <https://docs.python.org/2/library/functions.html#tuple>.

### Python Module Errors

MATLAB reports some Python errors as a MATLAB error loading a module. For more information, see “Undefined variable “py” or function “py.command”” on page 1-70.

If you write your own Python modules or modify the source code from an existing module, test your MATLAB commands by writing the equivalent Python command in your

Python interpreter. This workflow is beyond the scope of MATLAB documentation and product support.

## Errors Converting Python Data

When the data is compatible, MATLAB automatically converts Python data to MATLAB data. For the list of data types you must explicitly convert, see “Explicit Type Conversions” on page 1-60.

For example, although MATLAB supports multidimensional arrays, you can only pass vectors of data to Python.

```
x = py.len([2 3 4; 4 5 6])
```

```
Error using py.len  
Conversion of MATLAB 'double' to Python is only supported for 1-N vectors.
```

## More About

- “Data Types”
- “Limitations to Python Support” on page 1-68

## External Websites

- [www.python.org/doc](http://www.python.org/doc)

## Using Python Data in MATLAB

MATLAB automatically converts compatible Python data to MATLAB data.

For Python types that do not have compatible MATLAB types, such as `list` and `dict`, use the MATLAB functions shown in the Explicit Type Conversion table. This table also describes how to convert strings and certain numeric types explicitly.

### More About

- “Automatic Python Type to MATLAB Type Mapping” on page 1-60
- “Explicit Type Conversions” on page 1-60

## Call Python `eval` Function

This example shows how to evaluate the expression, `x+y`, in Python. To evaluate an expression, pass a Python `dict` value for the `globals` namespace parameter.

Read the help for `eval`.

```
py.help('eval')
```

```
Help on built-in function eval in module __builtin__:
```

```
eval(...)
```

```
eval(source[, globals[, locals]]) -> value
```

```
Evaluate the source in the context of globals and locals.
```

```
The source may be a string representing a Python expression
```

```
or a code object as returned by compile().
```

```
The globals must be a dictionary and locals can be any mapping,  
defaulting to the current globals and locals.
```

```
If only globals is given, locals defaults to it.
```

Create a Python `dict` variable for the `x` and `y` values.

```
workspace = py.dict(pyargs('x',1,'y',6))
```

```
workspace =
```

```
Python dict with no properties.
```

```
{'y': 6.0, 'x': 1.0}
```

Evaluate the expression.

```
res = py.eval('x+y',workspace)
```

```
res =
```

```
7
```

Add two numbers without assigning variables. Pass an empty `dict` value for the `globals` parameter.

```
res = py.eval('1+6',py.dict)
```

```
res =
```



7

## Precedence Order of Methods and Functions

If a Python class defines a method with the same name as a MATLAB converter method for Python types, MATLAB calls the Python method. This means you cannot call the MATLAB converter method on an object of that class.

For example, if a Python class defines a `char` method, the following statement calls the Python method.

```
char(obj)
```

To use the MATLAB `char` function, type:

```
char(py.str(obj))
```

# Python Function Arguments

## In this section...

“Positional Arguments” on page 1-81

“Keyword Arguments” on page 1-81

“Optional Arguments” on page 1-82

Your Python documentation shows you how to call a Python function. Python function signatures look similar to MATLAB function signatures. However, Python has syntax which might be unfamiliar to MATLAB users.

## Positional Arguments

A *positional* argument is passed by position. These arguments appear at the beginning of a function signature.

Python Signature	MATLAB Usage
abs(X)	py.abs(-99)
Argument X is required.	

Some functions accept an arbitrary sequence of positional arguments, including no arguments. In Python, these arguments are defined by prepending the name with the \* character.

Python Signature	MATLAB Usage
itertools.izip(*iterables)	Aggregate elements from two lists. py.itertools.izip(... py.list({1:10}),py.list({'a','b'}));
The <code>iterables</code> argument is not required, in which case, the function returns a zero length iterator.	Create zero length iterator. py.itertools.izip;

## Keyword Arguments

A *keyword* argument is preceded by an identifier. Keyword arguments, also called *named* arguments, can be specified in any order.

Keyword arguments are like name-value pairs in MATLAB. Use the MATLAB `pyargs` function to create keyword arguments for Python functions.

Python Signature	MATLAB Usage
<pre>print(*objects, sep=' ', end='\n', file=sys.stdout)</pre> <p><code>sep</code>, <code>end</code>, and <code>file</code> are keyword arguments.</p>	<p>Change the value of <code>end</code>.</p> <pre>py.print('string', pyargs('end', '--'))</pre>

Python defines an arbitrary number of keyword arguments by prepending the name with `**` characters.

Python Signature	MATLAB Usage
<pre>dict(**kwarg)</pre>	<pre>D = py.dict(pyargs('Joe', 100, 'Jack', 101))</pre>

## Optional Arguments

An *optional* argument is a non-required argument.

Python Signature	MATLAB Usage
<pre>random.randrange(start, stop[, step])</pre> <p>Argument <code>step</code> is optional.</p>	<pre>py.random.randrange(1, 100)</pre>

Optional arguments can have default values. A default value is indicated by an equal sign `=` with the default value.

Python Signature	MATLAB Usage
<pre>print(*objects, sep=' ', end='\n', file=sys.stdout)</pre> <p>The default value for <code>file</code> is <code>sys.stdout</code>.</p>	<p>Print two values using default keyword values.</p> <pre>py.print(2, '2')</pre>

## See Also

`pyargs`

## **Related Examples**

- “Pass Keyword Arguments” on page 1-34



# Read and Write MATLAB MAT-Files in C/C++ and Fortran

---

- “Custom Applications to Access MAT-Files” on page 2-2
- “MAT-File Library and Include Files” on page 2-5
- “What You Need to Build Custom Applications” on page 2-7
- “Copy External Data into MAT-File Format with Standalone Programs” on page 2-8
- “Create MAT-File in C or C++” on page 2-13
- “Read MAT-File in C/C++” on page 2-14
- “Create MAT-File in Fortran” on page 2-15
- “Read MAT-File in Fortran” on page 2-16
- “Work with mxArray” on page 2-17
- “Table of MAT-File Source Code Files” on page 2-19
- “Build on Mac and Linux Operating Systems” on page 2-21
- “Build on Windows Operating Systems” on page 2-23
- “Share MAT-File Applications” on page 2-24

## Custom Applications to Access MAT-Files

<b>In this section...</b>
“Why Write Custom Applications?” on page 2-2
“MAT-File Interface Library” on page 2-3
“Exchanging Data Files Between Platforms” on page 2-4

### Why Write Custom Applications?

To bring data into a MATLAB application, see “Methods for Importing Data”. To save data to a MAT-file, see “Save and Load Workspace Variables”. Use these procedures when you program your entire application in MATLAB, or if you share data with other MATLAB users. There are situations, however, when you must write a custom program to interact with data. For example:

- Your data has a custom format.
- You create applications for users who do not run MATLAB, and you want to provide them with MATLAB data.
- You want to read data from an external application, but you do not have access to the source code.

Before writing a custom application, determine if MATLAB meets your data exchange needs by reviewing the following topics:

- The `save` and `load` functions.
- “Supported File Formats for Import and Export”.
- The `importdata` function and “Import Images, Audio, and Video Interactively”.
- “Methods for Importing Data”.

If these features are not sufficient, you can create custom C/C++ or Fortran programs to read and write data files in the format required by your application. There are two types of custom programs:

- Standalone program — Run from a system prompt or execute in MATLAB (see “Run External Commands, Scripts, and Programs” on page 16-3). Requires MATLAB libraries to build the application.



- MEX file — Built and executed from the MATLAB command prompt. For information about creating and building MEX files, see “MEX File Creation API”.

## MAT-File Interface Library

The MAT-File Library contains routines for reading and writing MAT-files. Call these routines from your own C/C++ and Fortran programs. Use these routines, rather than attempt to write your own code, to perform these operations, since using the library insulates your applications from future changes to the MAT-file structure. For more information, see “MAT-File Library and Include Files” on page 2-5.

MATLAB provides the `MATFile` type for representing a MAT-file.

### MAT-File Routines

MAT-Function	Purpose
<code>matOpen</code>	Open a MAT-file.
<code>matClose</code>	Close a MAT-file.
<code>matGetDir</code>	Get a list of MATLAB arrays from a MAT-file.
<code>matGetVariable</code>	Read a MATLAB array from a MAT-file.
<code>matPutVariable</code>	Write a MATLAB array to a MAT-file.
<code>matGetNextVariable</code>	Read the next MATLAB array from a MAT-file.
<code>matDeleteVariable</code>	Remove a MATLAB array from a MAT-file.
<code>matPutVariableAsGlobal</code>	Put a MATLAB array into a MAT-file such that the <code>load</code> command places it into the global workspace.
<code>matGetVariableInfo</code>	Load a MATLAB array header from a MAT-file (no data).
<code>matGetNextVariableInfo</code>	Load the next MATLAB array header from a MAT-file (no data).

### MAT-File C-Only Routines

<code>matGetFp</code>	Get an ANSI <sup>®</sup> C file pointer to a MAT-file.
-----------------------	--

The MAT-File Interface Library does not support MATLAB objects created by user-defined classes.

Do not create different MATLAB sessions on different threads using MAT-File Library functions. MATLAB libraries are not multithread safe so you can use these functions only on a single thread at a time.

### Exchanging Data Files Between Platforms

You can work with MATLAB software on different computer systems and send MATLAB applications to users on other systems. MATLAB applications consist of MATLAB code containing functions and scripts, and MAT-files containing binary data.

Both types of files can be transported directly between machines: MATLAB source files because they are platform independent, and MAT-files because they contain a machine signature in the file header. MATLAB checks the signature when it loads a file and, if a signature indicates that a file is foreign, performs the necessary conversion.

Using MATLAB across different machine architectures requires a facility for exchanging both binary and ASCII data between the machines. Examples of this type of facility include FTP, NFS, and Kermit. When using these programs, be careful to transmit MAT-files in *binary file mode* and MATLAB source files in *ASCII file mode*. Failure to set these modes correctly corrupts the data.

## MAT-File Library and Include Files

MATLAB provides include and library files to write programs to read and write MAT-files. The following table lists the path names to these files. The term *matlabroot* refers to the root folder of your MATLAB installation. The term *arch* is a unique string identifying the platform.

### MAT-Function Folders

Platform	Contents	Folder
Microsoft Windows	Include files	<i>matlabroot</i> \extern\include
	Libraries	<i>matlabroot</i> \bin\win64
	Examples	<i>matlabroot</i> \extern\examples\eng_mat
Mac Linux	Include files	<i>matlabroot</i> /extern/include
	Libraries	<i>matlabroot</i> /bin/ <i>arch</i>
	Examples	<i>matlabroot</i> /extern/examples/ <i>eng_mat</i>

### MAT-Function Include Files

The *matlabroot*\extern\include folder holds header files containing function declarations with prototypes for the routines that you can access in the API Library. These files are the same for Windows, Mac, and Linux systems. The folder contains:

- The `matrix.h` header file that contains a definition of the `mxArray` structure and function prototypes for matrix access routines.
- The `mat.h` header file that contains function prototypes for `mat` routines.

### MAT-Function Libraries

The name of the libraries folder, which contains the shared (dynamically linkable) libraries, is platform-dependent.

#### Shared Libraries on Windows Systems

The `bin` folder contains the run-time version of the shared libraries:

- The `libmat.dll` library of MAT-file routines (C/C++ and Fortran)

- The `libmx.dll` library of array access and creation routines

### Shared Libraries on Mac and Linux Systems

The `bin/arch` folder, where *arch* is the value returned by the `computer('arch')` command, contains the shared libraries. For example, on Apple Macintosh 64-bit systems, the folder is `bin/maci64`:

- The `libmat.dylib` library of MAT-file routines (C/C++ and Fortran)
- The `libmx.dylib` library of array access and creation routines

### Example Files

The `examples/eng_mat` folder contains C/C++ and Fortran source code for examples demonstrating how to use the MAT-file routines.

## What You Need to Build Custom Applications

To create a custom application, you need the tools and knowledge to modify and build source code. In particular, you need a compiler supported by MATLAB.

To exchange custom data with MATLAB data, use a *MAT-file*, a MATLAB format binary file. You do not need the MAT-file format specifications because the MAT-File Interface Library provides the API to the data. You need to know the details of your data to map it into MATLAB data. Get this information from your product documentation, then use the `mxArray` type in the Matrix Library to declare the data in your program.

In your custom program, use functions in the MATLAB C/C++ and Fortran API:

- MAT-File Interface Library
- Matrix Library

To build the application, use the `mex` build script with the `-client engine` option.

### See Also

`mex` | `mxArray`

### More About

- “MAT-File Library and Include Files” on page 2-5
- “Build Engine Applications with IDE” on page 7-23

### External Websites

- Supported and Compatible Compilers

## Copy External Data into MAT-File Format with Standalone Programs

### In this section...

- “Overview of `matimport.c` Example” on page 2-8
- “Declare Variables for External Data” on page 2-9
- “Create `mxArray` Variables” on page 2-9
- “Create MATLAB Variable Names” on page 2-10
- “Read External Data into `mxArray` Data” on page 2-10
- “Create and Open MAT-File” on page 2-11
- “Write `mxArray` Data to File” on page 2-11
- “Clean Up” on page 2-11
- “Build the Application” on page 2-11
- “Create the MAT-File” on page 2-11
- “Import Data into MATLAB” on page 2-12

### Overview of `matimport.c` Example

This topic shows how to create a standalone program, `matimport`, to copy data from an external source into a MAT-file. The format of the data is custom, that is, it is not one of the file formats supported by MATLAB.

The `matimport.c` example:

- Creates variables to read the external data.
- Copies the data into `mxArray` variables.
- Assigns a variable name to each `mxArray`. Use these variable names in the MATLAB workspace.
- Writes the `mxArray` variables and associated variable names to the MAT-file.

To use the data in MATLAB:

- Build the standalone program `matimport`.
- Run `matimport` to create the MAT-file `matimport.mat`.

- Open MATLAB.
- Use one of the techniques described in “Save and Load Workspace Variables”.

The following topics describe these steps in detail. To see the code, open the file in the MATLAB Editor. The C statements in these topics are code snippets shown to illustrate a task. The statements in the topics are not necessarily sequential in the source file.

## Declare Variables for External Data

There are two external data values, a string and an array of type double. The following table shows the relationship between the variables in this example.

External Data	Variable to Read External Data	mxArray Variable	MATLAB Variable Name
Array of type double	extData	pVarNum	inputArray
String	extString	pVarChar	titleString

The following statements declare the type and size for variables `extString` and `extData`:

```
#define BUFSIZE 256
char extString[BUFSIZE];
double extData[9];
```

Use these variables to read values from a file or a subroutine available from your product. This example uses initialization to create the external data:

```
const char *extString = "Data from External Device";
double extData[9] = { 1.0, 4.0, 7.0, 2.0, 5.0, 8.0, 3.0, 6.0, 9.0 };
```

## Create mxArray Variables

The MAT-File Library uses pointers of type `mxArray` to reference MATLAB data. The following statements declare `pVarNum` and `pVarChar` as pointers to an array of any size or type:

```
/*Pointer to the mxArray to read variable extData */
mxArray *pVarNum;
/*Pointer to the mxArray to read variable extString */
```

```
mxAarray *pVarChar;
```

To create a variable of the proper size and type, select one of the `mxCreat*` functions from the MX Matrix Library.

The size of `extData` is 9, which the example copies into a 3-by-3 matrix. Use the `mxCreatedoubleMatrix` function to create a two-dimensional, double-precision, floating-point `mxAarray` initialized to 0.

```
pVarNum = mxCreatedoubleMatrix(3,3,mxREAL);
```

Use the `mxCreatestring` function to create an `mxAarray` variable for `extString`:

```
pVarChar = mxCreatestring(extString);
```

### Create MATLAB Variable Names

`matimport.c` assigns variable names `inputArray` and `titleString` to the `mxAarray` data. Use these names in the MATLAB workspace. For more information, see “View Contents of MAT-File”.

```
const char *myDouble = "inputArray";  
const char *myString = "titleString";
```

### Read External Data into `mxAarray` Data

Copy data from the external source into each `mxAarray`.

The C `memcpy` function copies blocks of memory. This function requires pointers to the variables `extData` and `pVarNum`. The pointer to `extData` is `(void *)extData`. To get a pointer to `pVarNum`, use one of the `mxCreat*` functions from the MX Matrix Library. Since the data contains only real values of type `double`, this example uses the `mxCreatPr` function:

```
memcpy((void *)mxCreatPr(pVarNum), (void *)extData, sizeof(extData));
```

The following statement initializes the `pVarChar` variable with the contents of `extString`:

```
pVarChar = mxCreatestring(extString);
```

Variables `pVarNum` and `pVarChar` now contain the external data.



## Create and Open MAT-File

The `matOpen` function creates a handle to a file of type `MATFile`. The following statements create a file pointer `pmat`, name the file `matimport.mat`, and open it for writing:

```
MATFile *pmat;  
const char *myFile = "matimport.mat";  
pmat = matOpen(myFile, "w");
```

## Write mxArray Data to File

The `matPutVariable` function writes the `mxArray` and variable name into the file:

```
status = matPutVariable(pmat, myDouble, pVarNum);  
status = matPutVariable(pmat, myString, pVarChar);
```

## Clean Up

To close the file:

```
matClose(pmat);
```

To free memory:

```
mxDestroyArray(pVarNum);  
mxDestroyArray(pVarChar);
```

## Build the Application

To build the application, use the `mex` function with the `-client` engine option.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'eng_mat', 'matimport.c'), '.', 'f')  
mex -v -client engine matimport.c
```

## Create the MAT-File

Run `matimport` to create the file `matimport.mat`. Either invoke the program from the system command prompt, or at the MATLAB command prompt, type:

```
!matimport
```

### Import Data into MATLAB

Any user with a compatible version of MATLAB can read the `matimport.mat` file. Start MATLAB and use the `load` command to import the data into the workspace:

```
load matimport.mat
```

To see the variables, type `whos`; MATLAB displays:

Name	Size	Bytes	Class
<code>inputArray</code>	3x3	72	double
<code>titleString</code>	1x43	86	char

### Related Examples

- “Table of MAT-File Source Code Files” on page 2-19

## Create MAT-File in C or C++

### In this section...

“Create MAT-File in C” on page 2-13

“Create MAT-File in C++” on page 2-13

### Create MAT-File in C

The `matcreat.c` example illustrates how to use the library routines to create a MAT-file that you can load into the MATLAB workspace. The program also demonstrates how to check the return values of MAT-function calls for read or write failures. To see the code, open the file in MATLAB Editor.

After building the program, run the application. This program creates `mattest.mat`, a MAT-file that you can load into MATLAB. To run the application, depending on your platform, either double-click its icon or enter `matcreat` at the system prompt:

```
matcreat
Creating file mattest.mat...
```

To verify the MAT-file, at the command prompt, type:

```
whos -file mattest.mat
  Name              Size          Bytes  Class
  GlobalDouble      3x3            72  double array (global)
  LocalDouble       3x3            72  double array
  LocalString       1x43           86  char array
```

Grand total is 61 elements using 230 bytes

### Create MAT-File in C++

The C++ version of `matcreat.c` is `matcreat.cpp`. Open the file in MATLAB Editor.

### Related Examples

- “Table of MAT-File Source Code Files” on page 2-19

### Read MAT-File in C/C++

The `matdgn.c` example illustrates how to use the library routines to read and diagnose a MAT-file. To see the code, open the file in MATLAB Editor.

After building the program, run the application. This program reads the `mattest.mat` MAT-file created by the “Create MAT-File in C or C++” on page 2-13 example. To run the application, depending on your platform, either double-click its icon or enter `matdgn` at the system prompt.

```
matdgn mattest.mat
Reading file mattest.mat...
```

```
Directory of mattest.mat:
GlobalDouble
LocalString
LocalDouble
```

Examining the header for each variable:

```
According to its header, array GlobalDouble has 2 dimensions
    and was a global variable when saved
According to its header, array LocalString has 2 dimensions
    and was a local variable when saved
According to its header, array LocalDouble has 2 dimensions
    and was a local variable when saved
```

Reading in the actual array contents:

```
According to its contents, array GlobalDouble has 2 dimensions
    and was a global variable when saved
According to its contents, array LocalString has 2 dimensions
    and was a local variable when saved
According to its contents, array LocalDouble has 2 dimensions
    and was a local variable when saved
Done
```

### Related Examples

- “Create MAT-File in Fortran” on page 2-15
- “Table of MAT-File Source Code Files” on page 2-19

## Create MAT-File in Fortran

The `matdemo1.F` example creates the MAT-file, `matdemo.mat`. To see the code, you can open the file in MATLAB Editor.

After building the program, run the application. This program creates a MAT-file, `matdemo.mat`, that you can load into MATLAB. To run the application, depending on your platform, either double-click its icon or type `matdemo1` at the system prompt:

```
matdemo1
```

```
Creating MAT-file matdemo.mat ...
Done creating MAT-file
```

To verify the MAT-file, at the command prompt, type:

```
whos -file matdemo.mat
```

Name	Size	Bytes	Class	Attributes
Numeric	3x3	72	double	
NumericGlobal	3x3	72	double	global
String	1x33	66	char	

---

**Note:** For an example of a Microsoft Windows standalone program (not MAT-file specific), see `engwindemo.c` in the `matlabroot\extern\examples\eng_mat` folder.

---

### Related Examples

- “Read MAT-File in C/C++” on page 2-14
- “Table of MAT-File Source Code Files” on page 2-19

### Read MAT-File in Fortran

The `matdemo2.F` example illustrates how to use the library routines to read the MAT-file created by `matdemo1.F` and describe its contents. To see the code, open the file in MATLAB Editor.

After building the program, view the results:

```
matdemo2
Directory of Mat-file:
String
Numeric
Getting full array contents:
  1
Retrieved String
  With size  1-by- 33
  3
Retrieved Numeric
  With size  3-by- 3
```

### Related Examples

- “Table of MAT-File Source Code Files” on page 2-19

## Work with mxArray

### In this section...

“Read Structures from a MAT-File” on page 2-17

“Read Cell Arrays from a MAT-File” on page 2-18

The MAT-File Interface Library lets you access MATLAB arrays (type `mxArray`) in a MAT-file. To work directly with an `mxArray` in a C/C++ application, use functions in the Matrix Library.

You can find examples for working with the `mxArray` type in the `matlabroot/extern/examples/mex` and `matlabroot/extern/examples/mx` folders. The following topics show C code examples, based on these MEX examples, for working with cells and structures. The examples show how to read cell and structure arrays and display information based on the type of the `mxArray` within each array element.

If you create an application from one of the MEX examples, here are some tips for adapting the code to a standalone application.

- The MAT-file example, `matdgn.c`, shows how to open and read a MAT-file. For more information about the example, see “Read MAT-File in C/C++” on page 2-14.
- The MEX example, `explore.c`, has functions to read any MATLAB type using the `mxClassID` function. For more information about the example, see “Using Data Types” on page 4-12.
- Some MEX examples use functions, such as `mexPrintf`, from the “MEX Library API” `libmex`. You do not need to use these functions to work with an `mxArray`, but if your program calls any of them, you must link to the MEX Library. To do this, add `libmex.lib` to the link statement.

### Read Structures from a MAT-File

The `matreadstructarray.c` example is based on the `analyze_structure` function in `explore.c`. For simplicity, this example only processes real elements of type `double`; refer to the `explore.c` example for error checking and processing other types.

To see the code, open the file in the MATLAB Editor.

After building the program, run the application on the MAT-file, `testpatient.mat`.

First, create a structure, `patient`, and save it:

```
patient(1).name = 'John Doe';
patient(1).billing = 127.00;
patient(1).test = [79 75 73; 180 178 177.5; 172 170 169];
patient(2).name = 'Ann Lane';
patient(2).billing = 28.50;
patient(2).test = [68 70 68; 118 118 119; 172 170 169];

save testpatient.mat
```

To calculate the total of the `billing` field, type:

```
!matreadstruct testpatient.mat patient billing

Total for billing: 155.50
```

## Read Cell Arrays from a MAT-File

The `matreadcellarray.c` example is based on the `analyze_cell` function in `explore.c`.

To see the code, open the file in the MATLAB Editor.

After building the program, run the application on the MAT-file, `testcells.mat`.

First, create three cell variables and save:

```
cellvar = {'hello'; [2 3 4 6 8 9]; [2; 4; 5]};
structvar = {'cell with a structure'; patient; [2; 4; 5]};
multicellvar = {'cell with a cell'; cellvar; patient};

save testcells.mat cellvar structvar multicellvar
```

To display the `mxArray` type for the contents of cell `cellvar`, type:

```
!matreadcell testcells.mat cellvar

0: string
1: numeric class
2: numeric class
```

## Related Examples

- “Table of MAT-File Source Code Files” on page 2-19



## Table of MAT-File Source Code Files

The `matlabroot/extern/examples/eng_mat` folder contains C/C++ and Fortran source code for examples demonstrating how to use the MAT-file routines. These examples create standalone programs. The source code is the same for both Windows, Mac, and Linux systems.

To build a code example, first copy the file to a writable folder, such as `c:\work` on your Windows path:

```
copyfile(fullfile(matlabroot,'extern','examples','eng_mat',...
'filename'), fullfile('c:','work'))
```

where *filename* is the name of the source code file.

For build information, see:

- “MAT-File Library and Include Files” on page 2-5
- “Build on Mac and Linux Operating Systems” on page 2-21
- “Build on Windows Operating Systems” on page 2-23

Example	Description
<code>matcreat.c</code>	C program that demonstrates how to use the library routines to create a MAT-file that you can load into MATLAB.
<code>matcreat.cpp</code>	C++ version of the <code>matcreat.c</code> program.
<code>matdgn.c</code>	C program that demonstrates how to use the library routines to read and diagnose a MAT-file.
<code>matdemo1.F</code>	Fortran program that demonstrates how to call the MATLAB MAT-file functions from a Fortran program.
<code>matdemo2.F</code>	Fortran program that demonstrates how to use the library routines to read the MAT-file created by <code>matdemo1.F</code> and describe its contents.
<code>matimport.c</code>	C program based on <code>matcreat.c</code> used in the example for writing standalone applications.
<code>matreadstructarray.c</code>	C program based on <code>explore.c</code> to read contents of a structure array.
<code>matreadcellarray.c</code>	C program based on <code>explore.c</code> to read contents of a cell array.

For examples using the Matrix Library, see:

- “Table of MEX File Source Code Files” on page 5-24.
- The `explore.c` example described in “Using Data Types” on page 4-12.

## Build on Mac and Linux Operating Systems

### In this section...

“Setting Run-Time Library Path” on page 2-21

“Building the Application” on page 2-22

### Setting Run-Time Library Path

At run time, you must tell the Mac and Linux operating system where the API shared libraries reside by setting an environment variable. The Mac or Linux command you use and the values you provide depend on your shell and system architecture. The following table lists the name of the environment variable (*envvar*) and the value (*pathspec*) to assign to it. The term *matlabroot* refers to the root folder of your MATLAB installation.

Operating System	<i>envvar</i>	<i>pathspec</i>
64-bit Apple Mac	DYLD_LIBRARY_PATH	<i>matlabroot</i> /bin/ maci64: <i>matlabroot</i> /sys/os/ maci64
64-bit Linux	LD_LIBRARY_PATH	<i>matlabroot</i> /bin/ glnxa64: <i>matlabroot</i> /sys/os/ glnxa64

#### Using the C Shell

Set the library path using the command:

```
setenv envvar pathspec
```

Replace the terms *envvar* and *pathspec* with the appropriate values from the table. For example, on a Macintosh system use:

```
setenv DYLD_LIBRARY_PATH  
matlabroot/bin/maci64:matlabroot/sys/os/maci64
```

You can place these commands in a startup script, such as `~/ .cshrc`.

#### Using the Bourne Shell

Set the library path using the command:

```
envvar = pathspec:envvar  
export envvar
```

Replace the terms *envvar* and *pathspec* with the appropriate values from the table. For example, on a Macintosh system use:

```
DYLD_LIBRARY_PATH=matlabroot/bin/maci64:matlabroot/sys/os/maci64:$DYLD_LIBRARY_PATH  
export DYLD_LIBRARY_PATH
```

You can place these commands in a startup script such as `~/ .profile`.

## Building the Application

To compile and link the `matcreat.c` example, use the `mex` script with the `-client engine` option.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'eng_mat', 'matcreat.c'), '.', 'f')
```

Use the following command to build it:

```
mex -v -client engine matcreat.c
```

To modify the build instructions for your particular compiler, use the `-v -n` options to view the current compiler and linker settings. Then, modify the settings using the `mex varname=varvalue` option.

## See Also

`mex`

## Build on Windows Operating Systems

To compile and link MAT-file programs, use the `mex` script with the `-client engine` option.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'eng_mat', 'matcreat.c'), '.', 'f')
```

Use the following command to build it:

```
mex -v -client engine matcreat.c
```

To modify the build instructions for your particular compiler, use the `-v -n` options to view the current compiler and linker settings. Then, modify the settings using the `mex varname=varvalue` option.

### See Also

`mex`

### Related Examples

- “Build Windows Engine Application” on page 7-11

## Share MAT-File Applications

MATLAB requires shared library files for building any MAT-file application. You must also distribute the run-time versions of these files along with any MAT-file application that you deploy to another system. Install the appropriate libraries in the *matlabroot/bin/arch* folder.

### Library File Names by Operating System

Windows	Linux	Mac
libmat.dll	libmat.so	libmat.dylib
libmx.dll	libmx.so	libmx.dylib

In addition to these libraries, you must have all third-party library files that `libmat` requires. MATLAB uses these additional libraries to support Unicode<sup>®</sup> character encoding and data compression in MAT-files. These library files must reside in the same folder as `libmx`. Determine the libraries using the platform-specific methods described in the following table.

### Library Dependency Commands

Windows	Linux	Mac
See the following instructions for Dependency Walker	<code>ldd -d libmat.so</code>	<code>otool -L libmat.dylib</code>

On Windows systems, to find library dependencies, use the third-party product Dependency Walker. Dependency Walker is a free utility that scans Windows modules and builds a hierarchical tree diagram of all dependent modules. For each module found, it lists all the functions exported by that module, and which of those functions are called by other modules. Download the Dependency Walker utility from the website <http://www.dependencywalker.com/>. See <http://www.mathworks.com/matlabcentral/answers/92362-how-do-i-determine-which-libraries-my-mex-file-or-stand-alone-application-requires> for information on using the Dependency Walker.

Drag and drop the file *matlabroot/bin/win64/libmat.dll* into Depends window.

# Calling C Shared Library Functions from MATLAB

---

- “Call Functions in Shared Libraries” on page 3-2
- “Limitations to Shared Library Support” on page 3-8
- “Limitations Using Structures” on page 3-13
- “Module Not Found Error” on page 3-15
- “No Matching Signature Error” on page 3-16
- “MATLAB Terminates Unexpectedly When Calling Function in Shared Library” on page 3-17
- “Pass Arguments to Shared Library Functions” on page 3-18
- “Shared Library `shrlibsample`” on page 3-23
- “Pass String Arguments” on page 3-24
- “Pass Structures” on page 3-26
- “Pass Enumerated Types” on page 3-32
- “Pass Pointers” on page 3-34
- “Pass Arrays” on page 3-39
- “Iterate Through an Array” on page 3-43
- “Pointer Arguments” on page 3-46
- “Structure Arguments” on page 3-49
- “Explore `libstruct` Objects” on page 3-51
- “MATLAB Prototype Files” on page 3-52

## Call Functions in Shared Libraries

**In this section...**

“What Is a Shared Library?” on page 3-2

“Load and Unload Library” on page 3-3

“View Library Functions” on page 3-4

“Invoke Library Functions” on page 3-6

### What Is a Shared Library?

A shared library is a collection of functions dynamically loaded by an application at run time. This MATLAB interface supports libraries containing functions programmed in any language, provided the functions have a C interface. MATLAB supports dynamic linking on all supported platforms.

Platform	Shared Library	File Extension
Microsoft Windows	dynamic link library file	.dll
UNIX <sup>®</sup> and Linux	shared object file	.so
Apple Macintosh	dynamic shared library	.dylib

A shared library needs a *header file*, which provides *signatures* for the functions in the library. A function signature, or prototype, establishes the name of the function and the number and types of its parameters. Specify the full path of the shared library and its header file.

You need an installed MATLAB-supported C compiler. For an up-to-date list of supported compilers, see the Supported and Compatible Compilers website.

MATLAB accesses C routines built into external, shared libraries through a command-line interface. This interface lets you load an external library into MATLAB memory and access functions in the library. Although types differ between the two language environments, usually you can pass types to the C functions without converting. MATLAB converts for you.

Details about using a shared library are in the topics:



- “Load and Unload Library” on page 3-3
- “View Library Functions” on page 3-4
- “Invoke Library Functions” on page 3-6

If the library function passes arguments, you need to determine the data type passed to and from the function. For information about data, see:

- “Pass Arguments to Shared Library Functions” on page 3-18
- “Manually Convert Data Passed to Functions” on page 3-21
- “Pointer Arguments” on page 3-46
- “Structure Arguments” on page 3-49

When you are finished working with the shared library, it is important to unload the library to free memory.

For more information, see “Limitations to Shared Library Support” on page 3-8

## Load and Unload Library

To give MATLAB access to functions in a shared library, first load the library into memory. After you load the library, you can request information about library functions and call them directly from the MATLAB command line. When you no longer need the library, unload it from memory to conserve memory usage.

To load a shared library into MATLAB, use the `loadlibrary` function. The most common syntax is:

```
loadlibrary('shrlib', 'hfile')
```

where *shrlib* is the shared library file name, and *hfile* is the name of the header file containing the function prototypes.

---

**Note:** The header file provides signatures for the functions in the library and is a required argument for `loadlibrary`.

---

For example, load the `libmx` library that defines the MATLAB Matrix Library routines. The following command creates the full path for the library header file, `matrix.h`:

```
hfile = fullfile(matlabroot, 'extern', 'include', 'matrix.h');
```

To load the library, type:

```
loadlibrary('libmx', hfile)
```

Use the `unloadlibrary` function to unload the library and free up memory.

---

**Note:** If you call `loadlibrary` on a library that is already loaded, MATLAB displays a message, but does not reload the library. To determine if a library is loaded, use the `libisloaded` function.

---

## View Library Functions

### View Functions in Command Window

To display information about library functions in the MATLAB Command Window, use the `libfunctions` command. For example, to see what functions are available in the `libmx` library, type:

```
if not(libisloaded('libmx'))
    hfile = [matlabroot '\extern\include\matrix.h'];
    loadlibrary('libmx', hfile)
end
libfunctions libmx
```

MATLAB displays (in part):

Functions in library libmx:

<code>mxAAddField</code>	<code>mxGetScalar</code>
<code>mxArrayToString</code>	<code>mxGetString_730</code>
<code>mxCalcSingleSubscript_730</code>	<code>mxGetUserBits</code>
<code>mxMalloc</code>	<code>mxIsCell</code>
<code>mxCreateCellArray_730</code>	<code>mxIsChar</code>
<code>mxCreateCellMatrix_730</code>	<code>mxIsClass</code>
<code>.</code>	<code>.</code>
<code>:</code>	<code>:</code>
<code>.</code>	<code>.</code>

To view function signatures, use the `-full` switch. This option shows the MATLAB syntax for calling functions written in C. The types used in the parameter lists and

return values are MATLAB types, not C types. For more information on types, see “C and MATLAB Equivalent Types” on page 3-18. For example, at the command line enter:

```
list = libfunctions('libmx', '-full')
```

MATLAB displays (in part):

```
list =
' [int32, MATLAB array, cstring] mxAddField(MATLAB array, cstring) '
' [cstring, MATLAB array] mxArrayToString(MATLAB array) '
' [uint64, MATLAB array, uint64Ptr] mxCalcSingleSubscript_730(
MATLAB array, uint64, uint64Ptr) '
' lib.pointer mxCalloc(uint64, uint64) '
' [MATLAB array, uint64Ptr] mxCreateCellArray_730(uint64, uint64Ptr) '
' MATLAB array mxCreateCellMatrix_730(uint64, uint64) '
.
.
.
```

### View Functions in Window


To get information about functions in a library, use the `libfunctionsview` function. MATLAB opens a window to display the following information:

Heading	Description
Return Type	Types the method returns
Name	Function name
Arguments	Valid types for input arguments

To see the functions in the `libmx` library, type:

```
if not(libisloaded('libmx'))
    hfile = [matlabroot '\extern\include\matrix.h'];
    loadlibrary('libmx',hfile)
end
libfunctionsview libmx
```

MATLAB displays the following window:



Return Type	Name	Arguments
[int32, MATLAB array, cstring]	mxAddField	(MATLAB array, cstring)
[cstring, MATLAB array]	mxArrayToString	(MATLAB array)
[int32, MATLAB array, int32Ptr]	mxCalcSingleSubscript	(MATLAB array, int32, int32Ptr)
lib.pointer	mxCalloc	(uint32, uint32)
MATLAB array	mxClearScalarDoubleFlag	(MATLAB array)
[MATLAB array, int32Ptr]	mxCreateCellArray	(int32, int32Ptr)
MATLAB array	mxCreateCellMatrix	(int32, int32)
[MATLAB array, int32Ptr]	mxCreateCharArray	(int32, int32Ptr)
[MATLAB array, stringPtrPtr]	mxCreateCharMatrixFromStrings	(int32, stringPtrPtr)
MATLAB array	mxCreateDoubleMatrix	(int32, int32, mxComplexity)
MATLAB array	mxCreateDoubleScalar	(double)
[MATLAB array, int32Ptr]	mxCreateLogicalArray	(int32, int32Ptr)
MATLAB array	mxCreateLogicalMatrix	(uint32, uint32)
MATLAB array	mxCreateLogicalScalar	(bool)

The types used in the argument lists and return values are MATLAB types, not C types. For more information on types, see “C and MATLAB Equivalent Types” on page 3-18.

## Invoke Library Functions

After loading a shared library into the MATLAB workspace, use the `calllib` function to call functions in the library. The syntax for `calllib` is:

```
calllib('libname', 'funcname', arg1, ..., argN)
```

Specify the library name, function name, and, if required, any arguments that get passed to the function.

The following example calls functions from the `libmx` library. To load the library, type:

```
if not(libisloaded('libmx'))
    hfile = [matlabroot '\extern\include\matrix.h'];
    loadlibrary('libmx', hfile)
end
```

To create an array `y`, type:

```
y = rand(4,7,2);
```

To get information about `y`, type:

```
calllib('libmx','mxGetNumberOfElements',y)
```

```
ans =  
    56
```

MATLAB displays the number of elements in the array.

Type:

```
calllib('libmx','mxGetClassID',y)
```

```
ans =  
    mxDOUBLE_CLASS
```

MATLAB displays the class of the array.

For information on how to define the parameter types, see “Pass Arguments to Shared Library Functions” on page 3-18.

## Limitations to Shared Library Support

### In this section...

“MATLAB Supports C Library Routines” on page 3-8

“Workarounds for Loading C++ Libraries” on page 3-8

“Limitations Using `printf` Function” on page 3-9

“Bit Fields” on page 3-9

“Enum Declarations” on page 3-10

“Unions Not Supported” on page 3-10

“Compiler Dependencies” on page 3-11

“Limitations Using Pointers” on page 3-11

“Functions with Variable Number of Input Arguments Not Supported” on page 3-12

## MATLAB Supports C Library Routines

The MATLAB shared library interface supports C library routines only. Most professionally written libraries designed to be used by multiple languages and platforms work fine. Many homegrown libraries or libraries that have only been tested from C++ have interfaces that are not usable and require modification or an interface layer. In this case, we recommend using MEX-files.

## Workarounds for Loading C++ Libraries

The shared library interface does not support C++ classes or overloaded functions elements. However, if you have source code for the library, you can apply one of the following strategies to load a C++ library using `loadlibrary`. After editing the source code, rebuild the library.

### Declare Functions as `extern "C"`

For example, the following function prototype from the file `shrlibsample.h` shows the syntax to use for each function:

```
#ifdef __cplusplus
extern "C" {
#endif
```

```

void addMixedTypes(
    short x,
    int y,
    double z
);

/* other prototypes may be here */

#ifdef __cplusplus
}
#endif

```

The following C++ code is not legal C code for the header file:

```
extern "C" void addMixedTypes(short x,int y,double z);
```

### Add Module Definition File in Visual Studio

While building the DLL from C++ code in Microsoft Visual Studio<sup>®</sup>, add a Module Definition File (.DEF) in the project. At a minimum, the DEF file must contain the following module-definition statements:

- The first statement in the file must be the LIBRARY statement.
- The EXPORTS statement lists the names and, optionally, the ordinal values of the functions exported by the DLL.

For example, if a DLL exports functions `multDoubleArray` and `addMixedTypes`, `module.def` contains:

```

LIBRARY
EXPORTS
multDoubleArray
addMixedTypes

```

### Limitations Using printf Function

MATLAB does not display the output of the C `printf` function to the command window.

### Bit Fields

You can modify a bit field declaration by using type `int` or an equivalent. For example, if your library has the following declared in its header file:

```
int myfunction();

struct mystructure
{
    /* note the sum of fields bits */
    unsigned field1 :4;
    unsigned field2 :4;
};
```

edit the header file and replace it with:

```
int myfunction();

struct mystructure
{
    /* field 8 bits wide to be manipulated in MATLAB */
    /* A char is 8 bits on all supported platforms */
    char allfields;
};
```

After editing the source code, rebuild the library. It is then possible to access the data in the two fields using bit masking in MATLAB.

## Enum Declarations

char definitions for enum are not supported. In C, a char constant, for example 'A', is automatically converted to its numeric equivalent (65). MATLAB does not convert constants. To use this type of enum, edit the header file by replacing 'A' with the number 65 (`int8('A') == 65`). For example, replace:

```
enum Enum1 {ValA='A',ValB='B'};
```

with:

```
enum Enum1 {ValA=65,ValB=66};
```

then rebuild the library.

## Unions Not Supported

Unions are not supported. As a workaround, modify the source code taking out the union declaration and replacing it with the largest alternative. Then, to interpret the



results, write MATLAB code as needed. For example, edit the source code and replace the following union:

```
struct mystruct
{
    union
    {
        struct {char byte1,byte2;};
        short word;
    };
};
```

with:

```
struct mystruct
{
    short word;
};
```

where on a little-endian based machine, `byte1` is `mod(f,256)`, `byte2` is `f/256`, and `word=byte2*256+byte1`. After editing the source code, rebuild the library.

## Compiler Dependencies

Header files must be compatible with the supported compilers on a platform. For an up-to-date list of supported compilers, see the [Supported and Compatible Compilers website](#). You cannot load external libraries with explicit dependencies on other compilers.

## Limitations Using Pointers

### Function Pointers

The shared library interface does not support library functions that work with function pointers.

### Multilevel Pointers

Limited support for multilevel pointers and structures containing pointers. Using inputs and outputs and structure members declared with more than two levels of indirection is unsupported. For example, `double ***outp` translated to `doublePtrPtrPtr` is not supported.

### Functions with Variable Number of Input Arguments Not Supported

The shared library interface does not support library functions with variable number of arguments, represented by an ellipsis (. . .).

You can create multiple alias functions in a prototype file, one for each set of arguments used to call the function. For more information, see “MATLAB Prototype Files” on page 3-52.

### More About

- “Limitations Using Structures” on page 3-13

## Limitations Using Structures

### MATLAB Returns Pointers to Structures

MATLAB returns pointers to structures. Return by value is not supported.

### Structure Cannot Contain Pointers to Other Structures

Nested structures or structures containing a pointer to a structure are not supported. However, MATLAB can access an array of structures created in an external library.

### Requirements for MATLAB Structure Arguments

When you pass a MATLAB structure to an external library function, the field names must meet the following requirements.

- Every MATLAB field name must match a field name in the library structure definition.
- MATLAB structures cannot contain fields that are not in the library structure definition.
- If a MATLAB structure contains fewer fields than defined in the library structure, MATLAB sets undefined fields to zero.
- Field names are case-sensitive. For example, suppose that library `mylib` contains function `myfunc` with the following structure definition.

```
struct S {  
    double len;  
};
```

The field name is `len`. If you pass a structure to `myfunc` with the field name `Len`, MATLAB displays an error.

```
S.Len = 100;  
calllib('mylib', 'myfunc', S)
```

### Requirements for C struct Field Names

When MATLAB loads a C `struct` definition, the field names in MATLAB are not case-sensitive. For example, when you load a library containing the following definition, MATLAB does not create two fields.

```
struct S {  
    double Num;  
    double num;  
};
```

### **More About**

- “Limitations to Shared Library Support” on page 3-8

## Module Not Found Error

This error occurs when the shared library has dependencies which MATLAB cannot find.

On Windows systems, to find library dependencies, use the third-party product Dependency Walker. Dependency Walker is a free utility that scans Windows modules and builds a hierarchical tree diagram of all dependent modules. For each module found, it lists all the functions exported by that module, and which of those functions are called by other modules. Download the Dependency Walker utility from the website <http://www.dependencywalker.com/>. See <http://www.mathworks.com/matlabcentral/answers/92362-how-do-i-determine-which-libraries-my-mex-file-or-stand-alone-application-requires> for information on using the Dependency Walker.

## No Matching Signature Error

This error occurs when you call a function without the correct input or output arguments, or if there is an error in the function signature in the header file.

For example, the function signature for the `addStructByRef` function in `shrlibsample` is:

```
[double, c_structPtr] addStructByRef(c_structPtr)
```

Load the library.

```
addpath(fullfile(matlabroot, 'extern', 'examples', 'shrlib'))  
loadlibrary('shrlibsample')
```

Create a structure, and call `addStructByRef`.

```
struct.p1 = 4;  
struct.p2 = 7.3;  
struct.p3 = -290;
```

If you call the function without the input argument, MATLAB displays the error message.

```
[res,st] = calllib('shrlibsample','addStructByRef')
```

```
Error using calllib  
No method with matching signature.
```

The correct call is:

```
[res,st] = calllib('shrlibsample','addStructByRef',struct)
```

### See Also

[calllib](#) | [libfunctions](#)

## MATLAB Terminates Unexpectedly When Calling Function in Shared Library

Some shared libraries, compiled as Microsoft Windows 32-bit libraries, use a calling convention that is incompatible with the default MATLAB calling convention. The default calling convention for MATLAB and for Microsoft C and C++ compilers is `cdecl`. For more information, see the MSDN<sup>®</sup> Calling Conventions article.

If your library uses a different calling convention, create a `loadlibrary` prototype file and modify it with the correct settings, as described in <http://www.mathworks.com/matlabcentral/answers/96578-why-does-matlab-crash-when-i-make-a-function-call-on-a-dll-in-matlab-7-6-r2008a>.

### See Also

`loadlibrary`

### Related Examples

- Why does MATLAB crash when I make a function call on a DLL in MATLAB 7.6 (R2008a)?

### More About

- “MATLAB Prototype Files” on page 3-52

### External Websites

- Calling Conventions

## Pass Arguments to Shared Library Functions

**In this section...**

“C and MATLAB Equivalent Types” on page 3-18

“How MATLAB Displays Function Signatures” on page 3-20

“NULL Pointer” on page 3-21

“Manually Convert Data Passed to Functions” on page 3-21

### C and MATLAB Equivalent Types

The shared library interface supports all standard scalar C types. The following table shows these C types with their equivalent MATLAB types. MATLAB uses the type from the right column for arguments having the C type shown in the left column.

---

**Note:** All scalar values returned by MATLAB are of type double.

---

#### MATLAB Primitive Types

C Type	Equivalent MATLAB Type
char, byte	int8
unsigned char, byte	uint8
short	int16
unsigned short	uint16
int	int32
long (Windows)	int32, long
long (Linux)	int64, long
unsigned int	uint32
unsigned long (Windows)	uint32, long
unsigned long (Linux)	uint64, long



C Type	Equivalent MATLAB Type
float	single
double	double
char *	char array (1xn)
*char[]	cell array of character vectors

The following table shows how MATLAB maps C pointers (column 1) to the equivalent MATLAB function signature (column 2). Usually, you can pass a variable from the Equivalent MATLAB Type column to functions with the corresponding Argument Data Type. See “Pointer Arguments in C Functions” on page 3-46 for information about when to use a `lib.pointer` object instead.

### MATLAB Extended Types

C Pointer Type	Argument Data Type	Equivalent MATLAB Type	Example Function in “Shared Library <code>shrlibsampl</code> ” on page 3-23
double *	doublePtr	double	addDoubleRef
float *	singlePtr	single	
intsize * (integer pointer types)	(u)int(size)Ptr For example, <code>int64 *</code> becomes <code>int64Ptr</code> .	(u)int(size)	multiplyShort
byte[]	int8Ptr	int8	
char[] (null-terminated string passed by value)	cstring	char array (1xn)	stringToUpper
char ** (array of pointers to strings)	stringPtrPtr	cell array of character vectors	
enum	enumPtr		
type **	typePtrPtr For example, <code>double **</code> becomes <code>doublePtrPtr</code> .	lib.pointer object	allocateStruct

C Pointer Type	Argument Data Type	Equivalent MATLAB Type	Example Function in “Shared Library <code>shrlibsampl</code> ” on page 3-23
<code>void *</code>	<code>voidPtr</code>		<code>deallocateStruct</code>
<code>void **</code>	<code>voidPtrPtr</code>	<code>lib.pointer</code> object	
<code>struct</code> (C-style structure)	<i>structure</i>	MATLAB <code>struct</code>	<code>addStructFields</code>
<code>mxArray *</code>	MATLAB array	MATLAB array	
<code>mxArray **</code>	MATLAB <code>arrayPtr</code>	<code>lib.pointer</code> object	

## How MATLAB Displays Function Signatures

Here are things to note about the input and output arguments shown in MATLAB function signatures.

- Many arguments (like `int32` and `double`) are similar to their C counterparts. In these cases, pass in the MATLAB types shown for these arguments.
- Some C arguments (for example, `**double`, or predefined structures), are different from standard MATLAB types. In these cases, either pass a standard MATLAB type and let MATLAB convert it for you, or convert the data yourself using the MATLAB functions `libstruct` and `libpointer`. For more information, see “Manually Convert Data Passed to Functions” on page 3-21.
- C functions often return data in input arguments passed by reference. MATLAB creates additional output arguments to return these values. Input arguments ending in `Ptr` or `PtrPtr` are also listed as outputs.

For an example of MATLAB function signatures, see “Shared Library `shrlibsampl`” on page 3-23.

### Guidelines for Passing Arguments

- Nonscalar arguments must be declared as passed by reference in the library functions.
- If the library function uses single subscript indexing to reference a two-dimensional matrix, keep in mind that C programs process matrices row by row. MATLAB

processes matrices by column. To get C behavior from the function, transpose the input matrix before calling the function, and then transpose the function output.

- Use an empty array, `[]`, to pass a NULL parameter to a library function that supports optional input arguments. This notation is valid only when the argument is declared as a `Ptr` or `PtrPtr` as shown by `libfunctions` or `libfunctionsview`.

## NULL Pointer

You can create a NULL pointer to pass to library functions in the following ways:

- Pass an empty array `[]` as the argument.
- Use the `libpointer` function:

```
p = libpointer; % no arguments
```

```
p = libpointer('string') % string argument
```

```
p = libpointer('cstring') % pointer to a string argument
```

- Use the `libstruct` function:

```
p = libstruct('structtype'); % structure type
```

### Empty `libstruct` Object

To create an empty `libstruct` object, call `libstruct` with only the `structtype` argument. For example:

```
sci = libstruct('c_struct')
get(sci)
```

```
p1: 0
p2: 0
p3: 0
```

MATLAB displays the initialized values.

## Manually Convert Data Passed to Functions

Under most conditions, MATLAB software automatically converts data passed to and from external library functions to the type expected by the external function. However, you might choose to convert your argument data manually. For example:

- When passing the same data to a series of library functions, convert it once manually before calling the first function rather than having MATLAB convert it automatically on every call. This strategy reduces the number of unnecessary copy and conversion operations.
- When passing large structures, save memory by creating MATLAB structures that match the shape of the C structures used in the function instead of using generic MATLAB structures. The `libstruct` function creates a MATLAB structure modeled from a C structure taken from the library.
- When an argument to an external function uses more than one level of referencing (for example, `double **`), pass a pointer created using the `libpointer` function rather than relying on MATLAB to convert the type automatically.

### See Also

`libfunctions` | `libfunctionsview` | `libpointer` | `libstruct`

### Related Examples

- “Shared Library `shrlibsampl`” on page 3-23

### More About

- “Structure Arguments” on page 3-49

## Shared Library `shrlibsample`

MATLAB includes a sample external library called `shrlibsample`. The library is in the folder `matlabroot\extern\examples\shrlib`.

View the source code in MATLAB.

```
edit([matlabroot ' /extern/examples/shrlib/shrlibsample.c'])
edit([matlabroot ' /extern/examples/shrlib/shrlibsample.h'])
```

To use the `shrlibsample` library, choose one of the following.

- Add the folder to your MATLAB path:

```
addpath(fullfile(matlabroot, 'extern', 'examples', 'shrlib'))
```

- Make the folder your current working folder:

```
cd(fullfile(matlabroot, 'extern', 'examples', 'shrlib'))
```

Load the library and display the MATLAB signatures for the functions in the library.

```
loadlibrary('shrlibsample')
libfunctions shrlibsample -full
```

Functions in library `shrlibsample`:

```
[double, doublePtr] addDoubleRef(double, doublePtr, double)
double addMixedTypes(int16, int32, double)
[double, c_structPtr] addStructByRef(c_structPtr)
double addStructFields(c_struct)
c_structPtrPtr allocateStruct(c_structPtrPtr)
voidPtr deallocateStruct(voidPtr)
lib.pointer exportedDoubleValue
lib.pointer getListOfStrings
doublePtr multDoubleArray(doublePtr, int32)
[lib.pointer, doublePtr] multDoubleRef(doublePtr)
int16Ptr multiplyShort(int16Ptr, int32)
doublePtr print2darray(doublePtr, int32)
printExportedDoubleValue
cstring readEnum(Enum1)
[cstring, cstring] stringToUpper(cstring)
```

## Pass String Arguments

### In this section...

“stringToUpper Function” on page 3-24

“Convert MATLAB Character Array to Uppercase” on page 3-24

### stringToUpper Function

The `stringToUpper` function in the `shrllibsample` library converts the characters in the input argument to uppercase. The input parameter, `char *`, is a C pointer to a string.

```
EXPORTED_FUNCTION char* stringToUpper(char *input)
{
    char *p = input;

    if (p != NULL)
        while (*p!=0)
            *p++ = toupper(*p);
    return input;
}
```

The function signature for `stringToUpper` is shown in the following table. MATLAB maps the C pointer type (`char *`) into `cstring` so you can pass a MATLAB character array to the function.

Return Type	Name	Arguments
[ <code>cstring</code> , <code>cstring</code> ]	<code>stringToUpper</code>	( <code>cstring</code> )

### Convert MATLAB Character Array to Uppercase

This example shows how to pass a MATLAB character array `str` to a C function, `stringToUpper`.

```
str = 'This was a Mixed Case string';
```

Load the library containing the `stringToUpper` function.

```
if not(libisloaded('shrllibsample'))
```

```
    addpath(fullfile(matlabroot,'extern','examples','shrlib'))
    loadlibrary('shrlibsample')
end
```

Pass `str` to the function.

```
res = calllib('shrlibsample','stringToUpper',str)
```

```
res =
```

```
THIS WAS A MIXED CASE STRING
```

The input parameter is a pointer to type `char`. However, a MATLAB character array is not a pointer, so the `stringToUpper` function does not modify the input argument, `str`.

```
str
```

```
str =
```

```
This was a Mixed Case string
```

## Related Examples

- “Shared Library `shrlibsample`” on page 3-23
- “Iterate Through an Array” on page 3-43

## Pass Structures

### In this section...

“addStructFields and addStructByRef Functions” on page 3-26

“Add Values of Fields in Structure” on page 3-27

“Preconvert MATLAB Structure Before Adding Values” on page 3-28

“Autoconvert Structure Arguments” on page 3-29

“Pass Pointer to Structure” on page 3-30

### addStructFields and addStructByRef Functions

The `shrlibsample` example library contains two functions with `c_struct` structure input parameters. `c_struct` is defined in the `shrlibsample.h` header file.

```
struct c_struct {
    double p1;
    short p2;
    long p3;
};
```

Both functions sum the values of the fields in the structure. The input to `addStructFields` is `c_struct`. The input to `addStructByRef` is a pointer to `c_struct`. This function also modifies the fields after summing the values.

#### addStructFields Function

The `addStructFields` function sums the values of the fields in a `c_struct` structure.

```
EXPORTED_FUNCTION double addStructFields(struct c_struct st)
{
    double t = st.p1 + st.p2 + st.p3;
    return t;
}
```

The MATLAB function signature is:

Return Type	Name	Arguments
double	addStructFields	(struct c_struct)



## addStructByRef Function

The `addStructByRef` function sums the values of the fields in a `c_struct` structure, then modifies the fields. The function returns the sum calculated before modifying the fields.

```
EXPORTED_FUNCTION double addStructByRef(struct c_struct *st) {
    double t = st->p1 + st->p2 + st->p3;
    st->p1 = 5.5;
    st->p2 = 1234;
    st->p3 = 12345678;
    return t;
}
```

Since the function modifies the input argument, MATLAB also returns the input as an output argument of type `c_structPtr`. The MATLAB function signature is:

Return Type	Name	Arguments
[double, c_structPtr]	addStructByRef	(c_structPtr)

You can pass a MATLAB structure to the function and let MATLAB autoconvert the argument. Or you can pass a pointer to a structure, which avoids creating a copy of the structure.

## Add Values of Fields in Structure

This example shows how to pass a MATLAB structure to the function, `addStructFields`.

Create and initialize structure `sm`. Each field is of type `double`.

```
sm.p1 = 476;
sm.p2 = -299;
sm.p3 = 1000;
```

Load the library containing the `addStructFields` function.

```
if not(libisloaded('shrlibsample'))
    addpath(fullfile(matlabroot,'extern','examples','shrlib'))
    loadlibrary('shrlibsample')
end
```

Call the function. MATLAB automatically converts the fields of structure `sm` to the library definition for `c_struct`.

```
calllib('shrllibsample', 'addStructFields', sm)
```

```
ans =
```

```
1177
```

## Preconvert MATLAB Structure Before Adding Values

This example shows how to preconvert structure `sm` to `c_struct` before calling `addStructFields`. If you repeatedly pass `sm` to functions, preconverting eliminates the processing time required by MATLAB to autoconvert the structure for each function call.

Create and initialize a MATLAB structure.

```
sm.p1 = 476;  
sm.p2 = -299;  
sm.p3 = 1000;
```

Load the library containing the `addStructFields` function.

```
if not(libisloaded('shrllibsample'))  
    addpath(fullfile(matlabroot, 'extern', 'examples', 'shrllib'))  
    loadlibrary('shrllibsample')  
end
```

Convert the fields, which are of type `double`, to match the `c_struct` structure types, `double`, `short`, and `long`.

```
sc = libstruct('c_struct', sm);
```

Display the field names and values.

```
get(sc)  
  
p1: 476  
p2: -299  
p3: 1000
```

Add the field values.

```
calllib('shrllibsample', 'addStructFields', sc)
```

```
ans =
```

```
1177
```

## Autoconvert Structure Arguments

This example shows how to pass a MATLAB structure to a C library function, `addStructByRef`. When you pass the structure, MATLAB automatically converts the field types, but MATLAB also makes a copy of the fields.

Load the library.

```
if not(libisloaded('shrllibsample'))
    addpath(fullfile(matlabroot, 'extern', 'examples', 'shrllib'))
    loadlibrary('shrllibsample')
end
```

Create a structure.

```
S.p1 = 476;
S.p2 = -299;
S.p3 = 1000;
```

Call `addStructByRef`.

```
res = calllib('shrllibsample', 'addStructByRef', S)
```

```
res =
```

```
1177
```

MATLAB does not modify the contents of structure `S`, since it is not a pointer.

```
S
```

```
S =
```

```
struct with fields:
```

```
p1: 476  
p2: -299  
p3: 1000
```

## Pass Pointer to Structure

This example shows how calling the `addStructByRef` function with a pointer modifies the fields in the input argument.

```
if not(libisloaded('shrlibsample'))  
    addpath(fullfile(matlabroot,'extern','examples','shrlib'))  
    loadlibrary('shrlibsample')  
end
```

Create a structure of type `c_struct`.

```
S.p1 = 20;  
S.p2 = 99;  
S.p3 = 3;
```

Create a pointer `sp` to the structure.

```
sp = libpointer('c_struct',S);  
sp.Value
```

```
ans =
```

```
struct with fields:
```

```
p1: 20  
p2: 99  
p3: 3
```

Pass the pointer to the function.

```
res = calllib('shrlibsample','addStructByRef',sp)
```

```
res =
```

122

When you pass a pointer, the function modifies the fields in the structure it points to.

`sp.Value`

`ans =`

`struct with fields:`

```
p1: 5.5000
p2: 1234
p3: 12345678
```

## See Also

`libpointer` | `libstruct`

## Related Examples

- “Shared Library `shrlibsample`” on page 3-23

## More About

- “Strategies for Passing Structures” on page 3-49
- “Limitations Using Structures” on page 3-13

## Pass Enumerated Types

### In this section...

“readEnum Function” on page 3-32

“Display Enumeration Values” on page 3-32

### readEnum Function

The readEnum function in the shrllibsample library displays a string that matches the input argument.

```
EXPORTED_FUNCTION char* readEnum(TEnum1 val)
{
    static char outputs[][20] = {
        {"You chose en1"},
        {"You chose en2"},
        {"You chose en4"},
        {"enum not defined"},
        {"ERROR"} };

    switch (val) {
        case en1: return outputs[0];
        case en2: return outputs[1];
        case en4: return outputs[2];
        default : return outputs[3];
    }
    return outputs[4];
}
```

The function signature is:

Return Type	Name	Arguments
cstring	readEnum	(Enum1)

The values for the Enum1 input are defined in the shrllibsample.h header file.

```
typedef enum Enum1 {en1 = 1, en2, en4 = 4} TEnum1;
```

### Display Enumeration Values

This example shows how to pass enumeration values to the readEnum function in the shrllibsample library. Load the library.

```
if not(libisloaded('shrllibsample'))
    addpath(fullfile(matlabroot,'extern','examples','shrllib'))
    loadlibrary('shrllibsample')
end
```

In MATLAB, you can express an enumerated type as either the enumeration string or its equivalent numeric value. Call `readEnum` with a string argument.

```
calllib('shrllibsample','readEnum','en4')
```

```
ans =
```

```
You chose en4
```

Call `readEnum` with the equivalent numeric argument. The `Enum1` definition declares enumeration `en4` equal to 4.

```
calllib('shrllibsample','readEnum',4)
```

```
ans =
```

```
You chose en4
```

## Related Examples

- “Shared Library `shrllibsample`” on page 3-23

## Pass Pointers

### In this section...

“multDoubleRef Function” on page 3-34

“Pass Pointer of Type double” on page 3-34

“Create Pointer Offset from Existing lib.pointer Object” on page 3-35

“Multilevel Pointers” on page 3-36

“allocateStruct and deallocateStruct Functions” on page 3-36

“Pass Multilevel Pointer” on page 3-37

“Return Array of Strings” on page 3-37

### multDoubleRef Function

The multDoubleRef function in the shrllibsample library multiplies the input by 5.

```
EXPORTED_FUNCTION double *multDoubleRef(double *x)
{
    *x *= 5;
    return x;
}
```

The input is a pointer to a **double**, and the function returns a pointer to a **double**. The MATLAB function signature is:

Return Type	Name	Arguments
[lib.pointer, doublePtr]	multDoubleRef	(doublePtr)

### Pass Pointer of Type double

This example shows how to construct and pass a pointer to C function multDoubleRef.

Load the library containing the function.

```
if not(libisloaded('shrllibsample'))
    addpath(fullfile(matlabroot, 'extern', 'examples', 'shrllib'))
    loadlibrary('shrllibsample')
end
```



Construct a pointer, `Xptr`, to the input argument, `X`.

```
X = 13.3;
Xptr = libpointer('doublePtr',X);
```

Verify the contents of `Xptr`.

```
get(Xptr)

    Value: 13.3000
  DataType: 'doublePtr'
```

Call the function and check the results.

```
calllib('shrlibsampl', 'multDoubleRef', Xptr);
Xptr.Value
```

```
ans =

    66.5000
```

`Xptr` is a handle object. Copies of this handle refer to the same underlying object and any operations you perform on a handle object affect all copies of that object. However, `Xptr` is not a C language pointer. Although it points to `X`, it does not contain the address of `X`. The function modifies the `Value` property of `Xptr` but does not modify the value in the underlying object `X`. The original value of `X` is unchanged.

```
X
```

```
X =

    13.3000
```

## Create Pointer Offset from Existing `lib.pointer` Object

This example shows how to create a pointer to a subset of a MATLAB vector `X`. The new pointer is valid only as long as the original pointer exists.

Create a pointer to a vector.

```
X = 1:10;
xp = libpointer('doublePtr',X);
xp.Value
```

```
ans =
```

```
1 2 3 4 5 6 7 8 9 10
```

Use the `lib.pointer` plus operator (+) to create a pointer to the last six elements of X.

```
xp2 = xp + 4;
xp2.Value
```

```
ans =
```

```
5 6 7 8 9 10
```

## Multilevel Pointers

*Multilevel pointers* are arguments that have more than one level of referencing. A multilevel pointer type in MATLAB uses the suffix `PtrPtr`. For example, use `doublePtrPtr` for the C argument `double **`.

When calling a function that takes a multilevel pointer argument, use a `lib.pointer` object and let MATLAB convert it to the multilevel pointer.

## allocateStruct and deallocateStruct Functions

The `allocateStruct` function in the `shrlibsample` library takes a `c_structPtrPtr` argument.

```
EXPORTED_FUNCTION void allocateStruct(struct c_struct **val)
{
    *val=(struct c_struct*) malloc(sizeof(struct c_struct));
    (*val)->p1 = 12.4;
    (*val)->p2 = 222;
    (*val)->p3 = 333333;
}
```

The MATLAB function signatures are:

Return Type	Name	Arguments
c_structPtrPtr	allocateStruct	(c_structPtrPtr)
voidPtr	deallocateStruct	(voidPtr)

## Pass Multilevel Pointer

This example shows how to pass a multilevel pointer to a C function.

Load the library containing `allocateStruct` and `deallocateStruct`.

```
if not(libisloaded('shrllibsample'))
    addpath(fullfile(matlabroot, 'extern', 'examples', 'shrllib'))
    loadlibrary('shrllibsample')
end
```

Create a `c_structPtr` pointer.

```
sp = libpointer('c_structPtr');
```

Call `allocateStruct` to allocate memory for the structure.

```
res = calllib('shrllibsample', 'allocateStruct', sp)
```

```
res =
```

```
    struct with fields:
```

```
    p1: 12.4000
    p2: 222
    p3: 333333
```

Free the memory created by the `allocateStruct` function.

```
calllib('shrllibsample', 'deallocateStruct', sp)
```

## Return Array of Strings

Suppose that you have a library, `myLib`, with a function, `acquireString`, that reads an array of strings. The function signature is:

Return Type	Name	Arguments
char**	acquireString	(void)

```
char** acquireString(void)
```

The following **pseudo-code** shows how to manipulate the return value, an array of pointers to strings.

```
ptr = calllib(myLib, 'acquireString')
```

MATLAB creates a `lib.pointer` object `ptr` of type `stringPtrPtr`. This object points to the first string. To view other strings, increment the pointer. For example, to display the first three strings, type:

```
for index = 0:2
    tempPtr = ptr + index;
    tempPtr.Value
end

ans =
    'str1'
ans =
    'str2'
ans =
    'str3'
```

**See Also**  
`libpointer`

## Pass Arrays

### In this section...

“print2darray Function” on page 3-39  
 “Convert MATLAB Array to C-Style Dimensions” on page 3-39  
 “multDoubleArray Function” on page 3-40  
 “Preserve 3-D MATLAB Array” on page 3-41

### print2darray Function

The `print2darray` function in the `shrlibsample` library displays the values of a 2-D array with three columns and a variable number of rows. The `my2d` parameter is a two-dimensional array of `double`. The `len` parameter is the number of rows.

```
EXPORTED_FUNCTION void print2darray(double my2d[][3],int len)
{
    int indxi,indxj;
    for(indxi=0;indxi<len;++indxi)
    {
        for(indxj=0;indxj<3;++indxj)
        {
            mexPrintf("%10g",my2d[indxi][indxj]);
        }
        mexPrintf("\n");
    }
}
```

### Convert MATLAB Array to C-Style Dimensions

This example shows how to pass data stored columnwise in a MATLAB array to a C function that assumes a row-by-column format.

Load the library containing the `print2darray` function.

```
if not(libisloaded('shrlibsample'))
    addpath(fullfile(matlabroot,'extern','examples','shrlib'))
    loadlibrary('shrlibsample')
end
```

Create a MATLAB array with 4 rows and 3 columns.

```
m = reshape(1:12,4,3)
```

```
m =
```

```
     1     5     9
     2     6    10
     3     7    11
     4     8    12
```

Display the values. The first column is [1 4 7 10] instead of [1 2 3 4].

```
calllib('shrlibsampl', 'print2darray', m, 4)
```

```
     1     2     3
     4     5     6
     7     8     9
    10    11    12
```

Transpose `m` to get the desired result.

```
calllib('shrlibsampl', 'print2darray', m', 4)
```

```
     1     5     9
     2     6    10
     3     7    11
     4     8    12
```

## multDoubleArray Function

The `multDoubleArray` function in the `shrlibsampl` library multiplies each element of an array by three. The function uses a single subscript (linear indexing) to navigate the input array.

```
EXPORTED_FUNCTION void multDoubleArray(double *x, int size)
{
    /* Multiple each element of the array by 3 */
    int i;
    for (i=0; i<size; i++)
        *x++ *= 3;
}
```

The MATLAB function signature is:

Return Type	Name	Arguments
doublePtr	multDoubleArray	(doublePtr, int32)

## Preserve 3-D MATLAB Array

This example shows how a C function changes the dimensions of a MATLAB array, and how to restore its shape.

Load the library.

```
if not(libisloaded('shrllibsample'))
    addpath(fullfile(matlabroot,'extern','examples','shrllib'))
    loadlibrary('shrllibsample')
end
```

Create a 2-by-5-by-2 input array and display its dimensions.

```
vin = reshape(1:20,2,5,2);
vs = size(vin)
```

```
vs =
     2     5     2
```

Call `multDoubleArray` to multiply each element. Display the dimensions of the output.

```
vout = calllib('shrllibsample','multDoubleArray',vin,20);
size(vout)
```

```
ans =
     2    10
```

Restore the original shape.

```
vout = reshape(vout,vs);
size(vout)
```

ans =

2 5 2



## Iterate Through an Array

### In this section...

“Create Cell Array from lib.pointer Object” on page 3-43

“Perform Pointer Arithmetic on Structure Array” on page 3-44

### Create Cell Array from lib.pointer Object

This example shows how to create a MATLAB® cell array of character vectors, `m1StringArray`, from the output of the `getListOfStrings` function.

Load the `shrlibsample` library.

```
if not(libisloaded('shrlibsample'))
    addpath(fullfile(matlabroot,'extern','examples','shrlib'))
    loadlibrary('shrlibsample')
end
```

Call the `getListOfStrings` function to create an array of character vectors. The function returns a pointer to the array.

```
ptr = calllib('shrlibsample','getListOfStrings');
class(ptr)
```

```
ans =
```

```
lib.pointer
```

Create indexing variables to iterate through the arrays. Use `ptrindex` for the array returned by the function and `index` for the MATLAB array.

```
ptrindex = ptr;
index = 1;
```

Create the cell array of character vectors `m1StringArray`. Copy the output of `getListOfStrings` to the cell array.

```
% read until end of list (NULL)
while ischar(ptrindex.value{1})
    m1StringArray{index} = ptrindex.value{1};
```

```
% increment pointer
ptrindex = ptrindex + 1;
% increment array index
index = index + 1;
end
```

View the contents of the cell array.

```
mlStringArray
```

```
mlStringArray =
```

```
1×4 cell array
```

```
'String 1' 'String Two' '' 'Last string'
```

## Perform Pointer Arithmetic on Structure Array

This example shows how to use pointer arithmetic to access elements of a structure. The example creates a MATLAB structure, based on the `c_struct` definition in the `shrlibsample.h` header file.

Load the definition.

```
if not(libisloaded('shrlibsample'))
    addpath(fullfile(matlabroot,'extern','examples','shrlib'))
    loadlibrary('shrlibsample')
end
```

Create the MATLAB structure.

```
s = struct('p1',{1,2,3},'p2',{1.1,2.2,3.3},'p3',{0});
```

Create a pointer to the structure.

```
sptr = libpointer('c_struct',s);
```

Read the values of the first element.

```
v1 = sptr.Value
```

v1 =

struct with fields:

p1: 1  
p2: 1  
p3: 0

Read the values of the next element by incrementing the pointer.

```
sptr = sptr + 1;  
v2 = sptr.Value
```

v2 =

struct with fields:

p1: 2  
p2: 2  
p3: 0

## Pointer Arguments

### In this section...

“Pointer Arguments in C Functions” on page 3-46

“Put String into Void Pointer” on page 3-46

“Memory Allocation for External Library” on page 3-47

### Pointer Arguments in C Functions

Many functions in external libraries pass arguments by reference. When you pass by reference, you pass a *pointer* to the value. In the function signature, pointer arguments have names ending in `Ptr` and `PtrPtr`. Although MATLAB does not support passing by reference, you can create a MATLAB argument, called a *lib.pointer object*, that is compatible with a C pointer. This object is an instance of the `MATLAB` class.

Often, you can simply pass a MATLAB variable (passing an argument by value), even when the signature for that function declares the argument to be a pointer. There are times, however, when it is useful to pass a `lib.pointer`.

- You want to modify the data in the input arguments.
- You are passing large amounts of data, and you want to control when MATLAB makes copies of the data.
- The library stores and uses the pointer so you want the MATLAB function to control the lifetime of the `lib.pointer` object.

### Put String into Void Pointer

C represents characters as 8-bit integers. To use a MATLAB character array as an input argument, convert the string to the proper type and create a `voidPtr`. For example:

```
str = 'string variable';  
vp = libpointer('voidPtr',[int8(str) 0]);
```

The syntax `[int8(str) 0]` creates the null-terminated string required by the C function. To read the string, and verify the pointer type, enter:

```
char(vp.Value)  
vp.DataType
```

```
ans =
string variable
ans =
voidPtr
```

MATLAB automatically converts an argument passed by value into an argument passed by reference when the external function prototype defines the argument as a pointer. Call a function that takes a `voidPtr` to a string as an input argument using the following syntax.

```
func_name([int8(str) 0])
```

Although MATLAB converts the argument from a value to a pointer, it must be of the correct type.

## Memory Allocation for External Library

In general, MATLAB passes a valid memory address each time you pass a variable to a library function. Use a `lib.pointer` object in cases where the library stores the pointer and accesses the buffer over time. In these cases, ensure that MATLAB has control over the lifetime of the buffer and prevent copies of the data from being made. The following **pseudo-code** is an example of asynchronous data acquisition that shows how to use a `lib.pointer` in this situation.

Suppose an external library `myLib` has the following functions:

```
AcquireData(int points,short *buffer)
IsAquisitionDone(void)
```

where `buffer` is declared as follows:

```
short buffer[99]
```

First, create a `lib.pointer` to an array of 99 points:

```
BufferSize = 99;
pBuffer = libpointer('int16Ptr',zeros(BufferSize,1));
```

Then, begin acquiring data and wait in a loop until it is done:

```
calllib('myLib','AcquireData',BufferSize,pbuffer)
while (~calllib('myLib','IsAcquisitionDone'))
    pause(0.1)
```

```
end
```

The following statement reads the data in the buffer:

```
result = pBuffer.Value;
```

When the library is done with the buffer, clear the MATLAB variable:

```
clear pBuffer
```

#### **See Also**

`lib.pointer`

# Structure Arguments

## Structure Argument Requirements

When you pass a MATLAB structure to an external library function:

- Every MATLAB field name must match a field name in the library structure definition. Field names are case-sensitive.
- MATLAB structures cannot contain fields that are not in the library structure definition.
- If a MATLAB structure contains fewer fields than defined in the library structure, MATLAB sets undefined fields to zero.

You do not need to match the data types of numeric fields. The `calllib` function converts to the correct numeric type.

## Find Structure Field Names

To determine the name and data type of structure fields, you can:

- Consult the library documentation.
- Look at the structure definition in the library header file.
- Use the `libstruct` function.

## Strategies for Passing Structures

MATLAB automatically converts a structure to the library definition for that structure type. For most cases, such as working with small structures, this works fine.

However, when working with repeated calls that pass large structures, convert the structure manually before making any calls to external functions. You save processing time by converting the structure data only once at the start rather than at each function call. You can also save memory if the fields of the converted structure take up less space than the original MATLAB structure.

To convert manually, call the `libstruct` function to create a *libstruct object*. Although it is an object, it behaves like a MATLAB structure. The fields of the object are derived from an externally specified structure type.

### See Also

libstruct

### Related Examples

- “Add Values of Fields in Structure” on page 3-27
- “Preconvert MATLAB Structure Before Adding Values” on page 3-28

### More About

- “Limitations Using Structures” on page 3-13



## Explore libstruct Objects

This example shows how to display information about and modify a libstruct object, `c_struct`.

Load the `shrlibsample` library containing the `c_struct` definition.

```
if not(libisloaded('shrlibsample'))
    addpath(fullfile(matlabroot, 'extern', 'examples', 'shrlib'))
    loadlibrary('shrlibsample')
end
```

Create the libstruct object. Object `sc` is an instance of a MATLAB class called `lib.c_struct`.

```
sc = libstruct('c_struct')
```

```
sc =  
  
lib.c_struct
```

Set structure field values.

```
set(sc, 'p1', 100, 'p2', 150, 'p3', 200)
```

Display field values.

```
get(sc)  
  
p1: 100  
p2: 150  
p3: 200
```

Modify values using MATLAB field structure syntax.

```
sc.p1 = 23;  
get(sc)  
  
p1: 23  
p2: 150  
p3: 200
```

## MATLAB Prototype Files

### In this section...

- “When to Use Prototype Files” on page 3-52
- “How to Create Prototype Files” on page 3-52
- “How to Specify Thunk Files” on page 3-53
- “Deploy Applications That Use `loadlibrary`” on page 3-53
- “`loadlibrary` in Parallel Computing Environment” on page 3-53
- “Change Function Signature” on page 3-53
- “Rename Library Function” on page 3-53
- “Load Subset of Functions in Library” on page 3-53
- “Call Function with Variable Number of Arguments” on page 3-54

### When to Use Prototype Files

MATLAB provides a way to modify header file information by creating a *prototype file*, a file of MATLAB commands.

Like a header file, the prototype file contains the function signatures for the library. Here are some reasons for using a prototype file.

- To deploy applications that use `loadlibrary` (using MATLAB Compiler™).
- To use `loadlibrary` in a parallel computing environment (using Parallel Computing Toolbox™).
- To change signatures of the library functions.
- To rename some of the library functions.
- To use only a small percentage of the functions in the library you are loading.
- To use functions with a variable number of arguments.

You can change the prototypes by editing the prototype file and reloading the library.

### How to Create Prototype Files

To create a prototype file, use the `mfilename` option of the `loadlibrary` function.

## How to Specify Thunk Files

For information about default thunk file names, see `loadlibrary`. To change the name, use the `thunkfilename` option.

## Deploy Applications That Use `loadlibrary`

To deploy a MATLAB application that uses `loadlibrary`, using MATLAB Compiler:

- Create a prototype file.
- For 64-bit applications, specify a thunk file.
- Include all the relevant files when creating the project with `mcc`.

## `loadlibrary` in Parallel Computing Environment

To use `loadlibrary` in a parallel computing environment (using Parallel Computing Toolbox):

- Create a prototype file.
- For 64-bit applications, specify a thunk file.
- Make sure that all relevant files are accessible to all workers.

## Change Function Signature

Edit the prototype file, changing the `fcns.LHS` or `fcns.RHS` field for that function. This edit changes the types of arguments on the left-hand side or right-hand side, respectively.

## Rename Library Function

Edit the prototype file, defining the `fcns.alias` field for that function.

## Load Subset of Functions in Library

Edit the prototype file, commenting out the unused functions. This edit reduces the amount of memory required for the library.

### Call Function with Variable Number of Arguments

Create an alias function in a prototype file for each set of arguments you use to call the function.

# Intro to MEX-Files

---

- “Introducing MEX Files” on page 4-3
- “Using MEX Files” on page 4-4
- “MEX File Placement” on page 4-5
- “Use Help Files with MEX Files” on page 4-6
- “MATLAB Data” on page 4-7
- “Testing for Most-Derived Class” on page 4-15
- “Build MEX File” on page 4-17
- “Linking Multiple Files” on page 4-18
- “What You Need to Build MEX Files” on page 4-19
- “Change Default Compiler” on page 4-20
- “SDK "macosx10.8" cannot be located Error Message” on page 4-23
- “Custom Build with MEX Script Options” on page 4-24
- “Compiling MEX Files with the Microsoft Visual C++ IDE” on page 4-25
- “Call LAPACK and BLAS Functions” on page 4-26
- “Upgrade MEX Files to Use 64-Bit API” on page 4-35
- “Upgrade MEX Files to Use Graphics Objects” on page 4-46
- “Platform Compatibility” on page 4-51
- “Invalid MEX File Error” on page 4-52
- “Run MEX File You Receive from Someone Else” on page 4-53
- “MEX File Dependent Libraries” on page 4-54
- “Document Build Information in the MEX File” on page 4-55
- “Version Compatibility” on page 4-57
- “Getting Help When MEX Fails” on page 4-58
- “Compiling MEX File Fails” on page 4-60
- “Symbol mexFunction Unresolved or Not Defined” on page 4-62

- “MEX File Segmentation Fault” on page 4-63
- “MEX File Generates Incorrect Results” on page 4-64
- “Memory Management Issues” on page 4-65

## Introducing MEX Files

You can call your own C, C++, or Fortran subroutines from the MATLAB command line as if they were built-in functions. These programs, called binary *MEX files*, are dynamically linked subroutines that the MATLAB interpreter loads and executes. The MEX file contains only one function or subroutine, and its name is the MEX file name. To call a MEX file, use the name of the file, without the file extension.

For information about using a MEX file that someone else created, see “Call MEX File Functions”.

The term `mex` stands for “MATLAB executable” and has different meanings, as shown in the following table.

<b>MEX Term</b>	<b>Definition</b>
source MEX file	C, C++, or Fortran source code file.
binary MEX file	Dynamically linked subroutine executed in the MATLAB environment.
MEX function library	MATLAB C/C++ and Fortran API Reference library to perform operations in the MATLAB environment.
<code>mex</code> build script	MATLAB function to create a binary file from a source file.

### Related Examples

- “Create C Source MEX File” on page 5-18

### More About

- “Creating C++ MEX Files” on page 5-13
- “What You Need to Build MEX Files” on page 4-19

## Using MEX Files

Binary MEX files are subroutines produced from C/C++ or Fortran source code. They behave just like MATLAB scripts and built-in functions. To call a MEX file, use the name of the file, without the file extension. The calling syntax depends on the input and output arguments defined by the MEX file.

While scripts have a platform-independent extension `.m`, MATLAB identifies MEX files by platform-specific extensions. The following table lists the platform-specific extensions for MEX files.

### MEX File Platform-Dependent Extension

Platform	Binary MEX File Extension
Linux (64-bit)	mexa64
Apple Mac (64-bit)	mexmaci64
Windows (64-bit)	mexw64

You cannot use a binary MEX file on a platform if you compiled it on a different platform. Recompile the source code on the platform for which you want to use the MEX file. For information about using MEX S-functions, see your Simulink<sup>®</sup> documentation.



## MEX File Placement

Put your MEX files in a folder on the MATLAB path. Alternatively, run MATLAB from the folder containing the MEX file. MATLAB runs functions in the current working folder before functions on the path.

To see the current folders on your path, use the `path` function. You can add new folders to the path either by using the `addpath` function, or by selecting **File > SetPath** to edit the path.

### MEX Files on Windows Network Drives

Windows network drive file servers do not always report folder and file changes correctly. If you change a MEX file on a network drive and find that MATLAB does not use the latest changes, change folders away from and then back to the folder containing the file.

### See Also

`addpath` | `path`

## Use Help Files with MEX Files

You can document the behavior of your MEX files by writing a MATLAB script containing comment lines. The `help` command searches for a MATLAB script and displays the appropriate text.

For example, copy the following text from the `arrayProduct.c` MEX source file into a file, `arrayproduct.m`.

```
% arrayproduct.m Help file for arrayProduct MEX-file.  
% arrayProduct.c - example in MATLAB External Interfaces  
%  
% Multiplies an input scalar (multiplier)  
% times a 1xN matrix (inMatrix)  
% and outputs a 1xN matrix (outMatrix)  
%  
% The calling syntax is:  
%  
%   outMatrix = arrayProduct(multiplier, inMatrix)  
%  
  
% This is a MEX-file for MATLAB.  
% Copyright 2007-2014 The MathWorks, Inc.  
%
```

When you type:

```
help arrayproduct
```

MATLAB displays the comments.

### See Also

`help`

### Related Examples

- “Document Build Information in the MEX File” on page 4-55
- “Add Help for Your Program”

## MATLAB Data

### In this section...

“The MATLAB Array” on page 4-7

“Lifecycle of mxArray” on page 4-7

“Data Storage” on page 4-8

“MATLAB Types” on page 4-10

“Sparse Matrices” on page 4-11

“Using Data Types” on page 4-12

### The MATLAB Array

The MATLAB language works with a single object type: the MATLAB array. All MATLAB variables (including scalars, vectors, matrices, character arrays, cell arrays, structures, and objects) are stored as MATLAB arrays. In C/C++, the MATLAB array is declared to be of type `mxArray`. The `mxArray` structure contains the following information about the array:

- Its type
- Its dimensions
- The data associated with this array
- If numeric, whether the variable is real or complex
- If sparse, its indices and nonzero maximum elements
- If a structure or object, the number of fields and field names

To access the `mxArray` structure, use the API functions in the Matrix Library. These functions allow you to create, read, and query information about the MATLAB data in your MEX files. Matrix Library functions use the `mwSize` type to avoid portability issues and allow MEX source files to be compiled correctly on all systems.

### Lifecycle of mxArray

Like MATLAB functions, a MEX-file gateway routine on page 5-3 passes MATLAB variables by reference. However, these arguments are C pointers. A *pointer* to a variable is the *address* (location in memory) of the variable. MATLAB functions handle data

storage for you automatically. When passing data to a MEX-file, you use pointers, which follow specific rules for accessing and manipulating variables. For information about working with pointers, refer to a programming reference, such as *The C Programming Language* by Kernighan, B. W., and D. M. Ritchie.

---

**Note:** Since variables use memory, you need to understand how your MEX-file creates an `mxArray` and your responsibility for releasing (freeing) the memory. This is important to prevent memory leaks. The lifecycle of an `mxArray`—and the rules for managing memory—depends on whether it is an input argument, output argument, or local variable. The function you call to deallocate an `mxArray` depends on the function you used to create it, which is listed in the create function’s MX Matrix Library documentation.

---

### Input Argument `prhs`

An `mxArray` passed to a MEX-file through the `prhs` input parameter exists outside the scope of the MEX-file. Do not free memory for any `mxArray` in the `prhs` parameter. Additionally, `prhs` variables are read-only; do not modify them in your MEX-file.

### Output Argument `plhs`

If you create an `mxArray` (allocate memory and create data) for an output argument, the memory and data exist beyond the scope of the MEX-file. Do not free memory on an `mxArray` returned in the `plhs` output parameter.

### Local Variable

You allocate memory whenever you use an `mxCreate*` function to create an `mxArray` or when you call the `mxMalloc` and associated functions. After observing the rules for handling input and output arguments, the MEX-file should destroy temporary arrays and free dynamically allocated memory. To deallocate memory, use either `mxDestroyArray` or `mxFree`. Refer to the MX Matrix Library function documentation for information about which function to use.

### Data Storage

MATLAB stores data in a column-major (columnwise) numbering scheme, which is how Fortran stores matrices. MATLAB uses this convention because it was originally written in Fortran. MATLAB internally stores data elements from the first column first, then data elements from the second column second, and so on, through the last column.

For example, given the matrix:

```
a = ['house'; 'floor'; 'porch']
```

```
a =
    house
    floor
    porch
```

its dimensions are:


```
size(a)
```

```
ans =
     3     5
```

and its data is stored as:

h	f	p	o	l	o	u	o	r	s	o	c	e	r	h
---	---	---	---	---	---	---	---	---	---	---	---	---	---	---

If a matrix is N-dimensional, MATLAB represents the data in N-major order. For example, consider a three-dimensional array having dimensions 4-by-2-by-3. Although you can visualize the data as:



MATLAB internally represents the data for this three-dimensional array in the following order:

A	B	C	D	E	F	G	H	I	J	K	L	M	N	O	P	Q	R	S	T	U	V	W	X
0	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23

The `mxCalcSingleSubscript` function creates the offset from the first element of an array to the desired element, using N-dimensional subscripting.

## MATLAB Types

### Complex Double-Precision Matrices

The most common data type in MATLAB is the complex double-precision, nonsparse matrix. These matrices are of type `double` and have dimensions `m`-by-`n`, where `m` is the number of rows and `n` is the number of columns. The data is stored as two vectors of double-precision numbers—one contains the real data and one contains the imaginary data. The pointers to this data are referred to as `pr` (pointer to real data) and `pi` (pointer to imaginary data), respectively. A noncomplex matrix is one whose `pi` is `NULL`.

### Other Numeric Matrices

MATLAB supports single-precision floating-point and 8-, 16-, and 32-bit integers, both signed and unsigned. The data is stored in two vectors in the same manner as double-precision matrices.

### Logical Matrices

The logical data type represents a logical `true` or `false` state using the numbers `1` and `0`, respectively. Certain MATLAB functions and operators return logical `1` or logical `0` to indicate whether a certain condition was found to be true or not. For example, the statement `(5 * 10) > 40` returns a logical `1` value.

### MATLAB Strings

MATLAB strings are of type `char` and are stored the same way as unsigned 16-bit integers except there is no imaginary data component. Unlike C, MATLAB strings are not null terminated.

### Cell Arrays

Cell arrays are a collection of MATLAB arrays where each `mxArray` is referred to as a cell. Cell arrays allow MATLAB arrays of different types to be stored together. Cell arrays are stored in a similar manner to numeric matrices, except the data portion

contains a single vector of pointers to `mxArrays`. Members of this vector are called cells. Each cell can be of any supported data type, even another cell array.

## Structures

A 1-by-1 structure is stored in the same manner as a 1-by- $n$  cell array where  $n$  is the number of fields in the structure. Members of the data vector are called fields. Each field is associated with a name stored in the `mxArray`.

## Objects

Objects are stored and accessed the same way as structures. In MATLAB, objects are named structures with registered methods. Outside MATLAB, an object is a structure that contains storage for an additional class name that identifies the name of the object.

## Multidimensional Arrays

MATLAB arrays of any type can be multidimensional. A vector of integers is stored where each element is the size of the corresponding dimension. The storage of the data is the same as matrices.

## Empty Arrays

MATLAB arrays of any type can be empty. An empty `mxArray` is one with at least one dimension equal to zero. For example, a double-precision `mxArray` of type `double`, where  $m$  and  $n$  equal 0 and `pr` is `NULL`, is an empty array.

## Sparse Matrices

Sparse matrices have a different storage convention from full matrices in MATLAB. The parameters `pr` and `pi` are still arrays of double-precision numbers or logical values, but these arrays contain only nonzero data elements. `pi` contains data only if the sparse matrix is complex.

There are three additional parameters: `nzmax`, `ir`, and `jc`. Use the `mwSize` and `mwIndex` types when declaring variables for these parameters.

- `nzmax` is an integer that contains the length of `ir`, `pr`, and `pi`, if it exists. It is the maximum number of nonzero elements in the sparse matrix.
- `ir` points to an integer array of length `nzmax` containing the row indices of the corresponding elements in `pr` and `pi`.

- `jc` points to an integer array of length `n+1`, where `n` is the number of columns in the sparse matrix. Note that in C, the first element of an `mxArray` has an index of 0. The `jc` array contains column index information. If the `j`th column of the sparse matrix has any nonzero elements, `jc[j]` is the index into `ir`, `pr`, and `pi` of the first nonzero element in the `j`th column. Index `jc[j+1] - 1` contains the last nonzero element in that column. For the `j`th column of the sparse matrix, `jc[j]` is the total number of nonzero elements in all preceding columns. The last element of the `jc` array, `jc[n]`, is equal to `nnz`, the number of nonzero elements in the entire sparse matrix. If `nnz` is less than `nzmax`, more nonzero entries can be inserted into the array without allocating more storage.

## Using Data Types

You can write source MEX files, MAT-file applications, and engine applications in C/C++ that accept any class or data type supported by MATLAB (see “Data Types”). In Fortran, only the creation of double-precision `n`-by-`m` arrays and strings are supported. You use binary C/C++ and Fortran MEX files like MATLAB functions.

---

**Caution** MATLAB does not check the validity of MATLAB data structures created in C/C++ or Fortran using one of the Matrix Library create functions (for example, `mxCreateStructArray`). Using invalid syntax to create a MATLAB data structure can result in unexpected behavior in your C/C++ or Fortran program.

---

## Declaring Data Structures

To handle MATLAB arrays, use type `mxArray`. The following statement declares an `mxArray` named `myData`:

```
mxArray *myData;
```

To define the values of `myData`, use one of the `mxCreate*` functions. Some useful array creation routines are `mxCreateNumericArray`, `mxCreateCellArray`, and `mxCreateCharArray`. For example, the following statement allocates an `m`-by-1 floating-point `mxArray` initialized to 0:

```
myData = mxCreateDoubleMatrix(m, 1, mxREAL);
```

C/C++ programmers should note that data in a MATLAB array is in column-major order. (For an illustration, see “Data Storage” on page 4-8.) Use the MATLAB `mxGet*` array access routines to read data from an `mxArray`.



## Manipulating Data

The `mxGet*` array access routines get references to the data in an `mxArray`. Use these routines to modify data in your MEX file. Each function provides access to specific information in the `mxArray`. Some useful functions are `mxGetData`, `mxGetPr`, `mxGetM`, and `mxGetString`. Many of these functions have corresponding `mxSet*` routines to allow you to modify values in the array.

The following statements read the input `prhs[0]` into a C-style string `buf`.

```
char *buf;
int buflen;
int status;
buflen = mxGetN(prhs[0])*sizeof(mxChar)+1;
buf = mxMalloc(buflen);
status = mxGetString(prhs[0], buf, buflen);
```

## The explore Example

There is an example source MEX file included with MATLAB, called `explore.c`, that identifies the data type of an input variable. The source code for this example is in `matlabroot/extern/examples/mex`, where `matlabroot` represents the top-level folder where MATLAB is installed on your system.

---

**Note:** In platform-independent discussions that refer to folder paths, this documentation uses the UNIX convention. For example, a general reference to the `mex` folder is `matlabroot/extern/examples/mex`.

---

To build the example MEX file, first copy the file to a writable folder on your path.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'mex', 'explore.c'), '.', 'f')
```

Use the `mex` command to build the MEX file.

```
mex -largeArrayDims explore.c
```

Type:

```
x = 2;
explore(x)
```

-----

```
Name: prhs[0]
Dimensions: 1x1
Class Name: double
```

```
-----
(1,1) = 2
```

`explore` accepts any data type. Try using `explore` with these examples:

```
explore([1 2 3 4 5])
explore 1 2 3 4 5
explore({1 2 3 4 5})
explore(int8([1 2 3 4 5]))
explore {1 2 3 4 5}
explore(sparse(eye(5)))
explore(struct('name', 'Joe Jones', 'ext', 7332))
explore(1, 2, 3, 4, 5)
```

### More About

- “Data Types”

## Testing for Most-Derived Class

If you define functions that require inputs that are:

- MATLAB built-in types
- Not subclasses of MATLAB built-in types

use the following technique to exclude subclasses of built-in types from the input arguments.

- Define a cell array that contains the names of built-in types accepted by your function.
- Call `class` and `strcmp` to test for specific types in a MATLAB control statement.

The following code tests an input argument, `inputArg`:

```
if strcmp(class(inputArg),'single')
    % Call function
else
    inputArg = single(inputArg);
end
```

## Testing for a Category of Types

Suppose that you create a MEX function, `myMexFcn`, that requires two numeric inputs that must be of type `double` or `single`:

```
outArray = myMexFcn(a,b)
```

Define a cell array `floatTypes` that contains the words `double` and `single`:

```
floatTypes = {'double','single'};

% Test for proper types
if any(strcmp(class(a),floatTypes)) && ...
    any(strcmp(class(b),floatTypes))
    outArray = myMexFcn(a,b);
else
    % Try to convert inputs to avoid error
    ...
end
```

## Another Test for Built-In Types

You can use `isobject` to separate built-in types from subclasses of built-in types. The `isobject` function returns `false` for instances of built-in types. For example:

```
% Create a int16 array
a = int16([2,5,7,11]);
isobject(a)
```

```
ans =
     0
```

Determine if an array is one of the built-in integer types:

```
if isa(a, 'integer') && ~isobject(a)
    % a is a built-in integer type
    ...
end
```

## Build MEX File

This example shows how to build the example MEX file, `timestwo`. Use this example to verify the build configuration for your system.

To build a code example, first copy the file to a writable folder on your path.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'timestwo.c'), '.', 'f')
```

Use the `mex` command to build the MEX file.

```
mex timestwo.c
```

```
Building with 'Microsoft Visual C++ 2012 (C)'.  
MEX completed successfully.
```

This command creates the file `timestwo.ext`, where `ext` is the value returned by the `mexext` function.

The `timestwo` function takes a scalar input and doubles it. Call `timestwo` like a MATLAB function.

```
timestwo(4)
```

```
ans =  
     8
```

### See Also

`mex` | `mexext`

### More About

- “What You Need to Build MEX Files” on page 4-19
- “Upgrade MEX Files to Use 64-Bit API” on page 4-35

## Linking Multiple Files

You can combine multiple source files, object files, and file libraries to build a binary MEX file. List the additional files, with their file extensions, separated by spaces. The name of the MEX file is the name of the first file in the list.

The following command combines multiple files of different types into a binary MEX file called `circle.ext`, where `ext` is the extension corresponding to the current platform:

```
mex circle.c square.obj rectangle.c shapes.lib
```

For a Fortran files, type:

```
mex circle.F square.o rectangle.F shapes.o
```

You can use a software development tool like `MAKE` to manage MEX file projects involving multiple source files. Create a `MAKEFILE` that contains a rule for producing object files from each of your source files. Then invoke the `mex` build script to combine your object files into a binary MEX file. This method ensures that your source files are recompiled only when necessary.

## What You Need to Build MEX Files

To create a MEX file:

- Install a MATLAB-supported compiler.
- Assemble your functions and the MATLAB API functions into one or more C/C++ or Fortran source files.
- Write a gateway function in one of your source files.
- Use the MATLAB `mex` command, called a build script, to build a binary MEX file.
- Use your binary MEX file like any MATLAB function.

If you have multiple compilers installed on your system, see “Change Default Compiler” on page 4-20.

### See Also

`mex`

### Related Examples

- “Build MEX File” on page 4-17

### More About

- “C/C++ Matrix Library API”
- “Fortran Matrix Library API”
- “Troubleshoot MEX Files”

### External Websites

- Supported and Compatible Compilers

## Change Default Compiler

In this section...
“Windows Systems” on page 4-20
“Change Linux System Default Compiler” on page 4-21
“Use Non-Default Compiler on Mac Systems” on page 4-21
“Do Not Use mex -f optionsfile Syntax” on page 4-22

### Windows Systems

If you have multiple MATLAB-supported compilers for a language installed on your Windows system, MATLAB selects one as the default compiler. You can change the default using the `mex -setup language` command. If you have multiple compilers, MATLAB displays a message with links to set up a different compiler.

If you call `mex -setup` without the *language* argument, MATLAB displays links to the other supported languages. Select a link to change the default for building MEX files in that language. MATLAB maintains separate default compiler options for C language and C++ language files.

If you call `mex -setup` from an operating system prompt, MATLAB displays the same information. However, the messages do not contain links. Instead, MATLAB displays the appropriate `mex` command syntax for changing the default compiler. Copy the command and paste it into the operating system prompt.

The compiler you choose remains the default until you call `mex -setup` to select a different default.

### C Compilers

To change the default C compiler, at the MATLAB command prompt, type:

```
mex -setup
```

`mex -setup` defaults to information about the C compiler. Alternatively, type:

```
mex -setup c
```

### C++ Compilers

To change the default C++ compiler, type:



```
mex -setup cpp
```

## Change Linux System Default Compiler

MATLAB supports only one compiler for each language on Linux platforms. If you have multiple compilers installed, the default compiler might not be the MATLAB-supported compiler. You can either change the system default compiler for all applications, or select the MATLAB-supported compiler each time you run the `mex` command.

To determine the default gcc compiler for your system, in MATLAB, type:

```
!which gcc
```

### Change System \$PATH Variable

You can change the default compiler by editing the system \$PATH variable. When you change the path, this compiler becomes the default for all applications on your system.

To change the \$PATH variable, add the folder containing the MATLAB-supported compiler to the beginning of the path. Refer to your operating system documentation for the correct command to use.

### Select MATLAB-Supported Compiler When Running mex

To change the compiler in the `mex` command, set the `varname` variable. `varname` for the gcc compiler is `GCC`, in uppercase letters. For example, if the currently supported gcc compiler is version 4.7, and it is installed in the `/usr/bin/gcc-4.7` folder on your system, to build `timestwo.c`, type:

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'timestwo.c'), '.', 'f')  
mex -v GCC='/usr/bin/gcc-4.7' timestwo.c
```

Setting the compiler using the `mex` command does not change the system default compiler.

## Use Non-Default Compiler on Mac Systems

If you have multiple versions of Xcode installed on your system, MATLAB uses the compiler defined by the `Xcode.app` application. You can use the compiler from an `Xcode.X.app`, where `Xcode.X.app` is the name you used to save a previously-installed Xcode version.

Before starting MATLAB, from the Terminal type:

```
xcode-select -switch /Applications/Xcode.X.app/Contents/Developer
```

To see which Xcode MATLAB is using, at the Terminal type:

```
xcode-select -p
```

### **Do Not Use `mex -f optionsfile` Syntax**

The `mex` command `-f` option to specify a build configuration file will be removed in a future release. Instead, use the work flows described in this topic for specifying a compiler.

### **See Also**

`mex`

### **Related Examples**

- “Choose a C++ Compiler” on page 5-29

### **More About**

- “SDK "macosx10.8" cannot be located Error Message” on page 4-23

### **External Websites**

- Supported and Compatible Compilers

## SDK "macosx10.8" cannot be located Error Message

On Mac platforms, running the `mex` command with an out-of-date options file generates an error containing the following text:

```
SDK "macosx10.8" cannot be located.
```

To replace the options file, type:

```
cd(prefdir)
delete mex_C_mac64i.xml
mex -setup
```

## Custom Build with MEX Script Options

The `mex` build script is sufficient for building MEX files. Following are reasons that you might need more detailed information:

- You want to use an Integrated Development Environment (IDE), rather than the provided script, to build MEX files.
- You want to exercise more control over the build process than the script uses.

Use the `mex -v -n` options to display the build commands to configure an IDE. You can also use the `mex` script options to modify the build steps.

### Include Files

Header files for the MATLAB API (MEX files, engine, and MAT-files). These files are in the `matlabroot\extern\include` folder.

- `matrix.h`—C/C++ header file containing a definition of the `mxArray` structure and function prototypes for matrix access routines.
- `mex.h`—Header file for building C/C++ MEX files. Contains function prototypes for `mex` routines.
- `engine.h`—C/C++ header file for MATLAB engine programs. Contains function prototypes for engine routines.
- `mat.h`—C/C++ header file for programs accessing MAT-files. Contains function prototypes for `mat` routines.
- `fintrf.h`—Header file for building Fortran MEX files. Contains function prototypes for `mex` routines.

### See Also

`mex`

## Compiling MEX Files with the Microsoft Visual C++ IDE

---

**Note:** This topic provides information on how to compile source MEX files in the Microsoft Visual C++ IDE. It assumes that you know how to use the IDE. If you need more information, refer to the corresponding Microsoft documentation.

---

To build MEX files with the Microsoft Visual C++ integrated development environment:

- 1 Create a project and insert your MEX source files.
- 2 Create a `.def` file to export the MEX entry point. On the **Project** menu, click **Add New Item** and select **Module-Definition File (.def)**. For example:
 

```
LIBRARY MYFILE
EXPORTS mexFunction      <-- for a C MEX file
      or
EXPORTS _MEXFUNCTION    <-- for a Fortran MEX file
```
- 3 On the **Project** menu, click **Properties** for the project to open the property pages.
- 4 Under *C/C++ General* properties, add the MATLAB include folder, `matlab\extern\include`, as an additional include folder.
- 5 Under *C/C++ Preprocessor* properties, add `MATLAB_MEX_FILE` as a preprocessor definition.
- 6 Under *Linker General* properties, change the output file extension to `.mexw64`.
- 7 Locate the `.lib` files for the compiler you are using under `matlabroot\extern\lib\win64\microsoft`. Under *Linker Input* properties, add `libmx.lib`, `libmex.lib`, and `libmat.lib` as additional dependencies.
- 8 Under **Linker Input properties**, add the module definition (`.def`) file you created.
- 9 Under **Linker Debugging properties**, if you intend to debug the MEX file using the IDE, specify that the build generates debugging information. For more information about debugging, see “Debug on Microsoft Windows Platforms” on page 5-53.

If you are using a compiler other than the Microsoft Visual C++ compiler, the process for building MEX files is similar. In step 4, locate the `.lib` files for the compiler you are using in the folder `matlabroot\extern\lib\win64`.

## Call LAPACK and BLAS Functions

### In this section...

“What You Need to Know” on page 4-26

“Creating a MEX File Using LAPACK and BLAS Functions” on page 4-26

“Preserving Input Values from Modification” on page 4-28

“Passing Arguments to Fortran Functions from C/C++ Programs” on page 4-29

“Passing Arguments to Fortran Functions from Fortran Programs” on page 4-30

“Handling Complex Numbers in LAPACK and BLAS Functions” on page 4-31

“Modifying the Function Name on UNIX Systems” on page 4-34

### What You Need to Know

You can call a LAPACK or BLAS function using a MEX file. To create a MEX file, you need C/C++ or Fortran programming experience and the software resources (compilers and linkers) to build an executable file. It also is helpful to understand how to use Fortran subroutines. MATLAB provides the `mwlapack` and `mwblas` libraries in `matlabroot/extern/lib`. To work with complex numbers, use the conversion routines in the `fort.c` and `fort.h` files in `matlabroot/extern/examples/refbook`. To help you get started, there are source code examples in `matlabroot/extern/examples/refbook`.

### Creating a MEX File Using LAPACK and BLAS Functions

To call LAPACK or BLAS functions:

- 1 Create a source MEX file containing the `mexFunction` gateway routine.
- 2 Select a supported compiler for your platform.
- 3 Build a binary MEX file using the `mex` command with one or more of the following options:
  - Link your source file to one or both of the libraries, `mwlapack` and `mwblas`.
  - Use the `-largeArrayDims` option; the `mwlapack` and `mwblas` libraries only support 64-bit integers for matrix dimensions.

- If your function uses complex numbers, build your source file with `fort.c` and include the `fort.h` header file.

The following topics show how to use the `mex` command using the example `matrixMultiply.c`. To work with this file, copy it to a local folder. For example:

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'matrixMultiply.c'), '.')
```

The example files are read-only files. To modify an example, ensure that the file is writable by typing:

```
fileattrib('matrixMultiply.c', '+w')
```

### Building on Windows Platforms

There are compiler-specific versions of the libraries on the Windows platform. To link to a specific library, look at the `matlabroot/extern/lib/` folder and choose the path for your architecture and compiler.

For example, to link to the libraries for a Microsoft C/C++ compiler, create the following build command variables, `lapacklib` and `blaslib`. These variables identify the full path and file name of each library.

```
lapacklib = fullfile(matlabroot, 'extern', 'lib', computer('arch'), 'microsoft', ...
    'libmwlapack.lib');
blaslib = fullfile(matlabroot, 'extern', 'lib', computer('arch'), 'microsoft', ...
    'libmwblas.lib');
```

When you use a variable to identify the library, use the function syntax of the `mex` command. (For more information, see “Command vs. Function Syntax”.) To build `matrixMultiply.c`, which uses functions from the BLAS library, type:

```
mex('-v', '-largeArrayDims', 'matrixMultiply.c', blaslib)
```

To build a MEX file with functions that use complex numbers, see “Handling Complex Numbers in LAPACK and BLAS Functions” on page 4-31.

### Building on UNIX Platforms

To build the MEX file `matrixMultiply.c`, which uses functions from the BLAS library, type:

```
mex -v -largeArrayDims matrixMultiply.c -lmwblas
```

To build a MEX file with functions that use complex numbers, see “Handling Complex Numbers in LAPACK and BLAS Functions” on page 4-31.

### Testing the `matrixMultiply` MEX File

To run the `matrixMultiply` MEX file, type:

```
A = [1 3 5; 2 4 7];  
B = [-5 8 11; 3 9 21; 4 0 8];  
X = matrixMultiply(A,B)
```

```
X =  
    24    35   114  
    30    52   162
```

### Preserving Input Values from Modification

Many LAPACK and BLAS functions modify the values of arguments passed to them. It is good practice to make a copy of arguments you can modify before passing them to these functions. For information about how MATLAB handles arguments to the `mexFunction`, see “Managing Input and Output Parameters” on page 5-4.

#### Example — `matrixDivide.c`

The following example calls the LAPACK function `dgesv` that modifies its input arguments. The code in this example makes copies of `prhs[0]` and `prhs[1]`, and passes the copies to `dgesv` to preserve the contents of the input arguments.

To see the example, open the file in the MATLAB Editor. To create the MEX file, copy the source file to a writable folder.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'matrixDivide.c'), '.')
```

To build the file on Windows, type:

```
lapacklib = fullfile(matlabroot, 'extern', 'lib', computer('arch'), 'microsoft', ...  
    'libmwlpack.lib');  
mex('-v', '-largeArrayDims', 'matrixDivide.c', lapacklib)
```

To build the file on UNIX type:

```
mex -v -largeArrayDims matrixDivide.c -lmwlapack
```



To test, type:

```
A = [1 2; 3 4];
B = [5; 6];
X = matrixDivide(A,B)

X =
    -4.0000
     4.5000
```

## Passing Arguments to Fortran Functions from C/C++ Programs

The LAPACK and BLAS functions are written in Fortran. C/C++ and Fortran use different conventions for passing arguments to and from functions. Fortran functions expect the arguments to be passed by reference, while arguments to C/C++ functions are passed by value. When you pass by value, you pass a copy of the value. When you pass by reference, you pass a pointer to the value. A reference is also the address of the value.

When you call a Fortran subroutine, like a function from LAPACK or BLAS, from a C/C++ program, be sure to pass the arguments by reference. To do this, precede the argument with an ampersand (&), unless that argument is already a reference. For example, when you create a matrix using the `mxGetPr` function, you create a reference to the matrix and do not need the ampersand before the argument.

In the following code snippet, variables `m`, `n`, `p`, `one`, and `zero` need the `&` character to make them a reference. Variables `A`, `B`, `C`, and `chn` are pointers, which are references.

```
/* pointers to input & output matrices*/
double *A, *B, *C;
/* matrix dimensions */
mwSignedIndex m,n,p;
/* other inputs to dgemm */
char *chn = "N";
double one = 1.0, zero = 0.0;

/* call BLAS function */
dgemm(chn, chn, &m, &n, &p, &one, A, &m, B, &p, &zero, C, &m);
```

### Example — `matrixMultiply.c`

The `matrixMultiply.c` example calls `dgemm`, passing all arguments by reference. To see the source code, open the file in the MATLAB Editor. To build and run this example, see “Creating a MEX File Using LAPACK and BLAS Functions” on page 4-26.

## Passing Arguments to Fortran Functions from Fortran Programs

You can call LAPACK and BLAS functions from Fortran MEX files. The following example takes two matrices and multiplies them by calling the BLAS routine `dgemm`. To run the example, copy the code into the editor and name the file `callldgemm.F`.

```
#include "fintrf.h"

subroutine mexFunction(nlhs, plhs, nrhs, prhs)
mwPointer plhs(*), prhs(*)
integer nlhs, nrhs
mwPointer mxcreatedoublematrix
mwPointer mxgetpr
mwPointer A, B, C
mwSize mxgetm, mxgetn
mwSignedIndex m, n, p
mwSize numel
double precision one, zero, ar, br
character ch1, ch2

ch1 = 'N'
ch2 = 'N'
one = 1.0
zero = 0.0

A = mxgetpr(prhs(1))
B = mxgetpr(prhs(2))
m = mxgetm(prhs(1))
p = mxgetn(prhs(1))
n = mxgetn(prhs(2))

plhs(1) = mxcreatedoublematrix(m, n, 0.0)
C = mxgetpr(plhs(1))
numel = 1
call mxcopyprtoreal8(A, ar, numel)
call mxcopyprtoreal8(B, br, numel)

call dgemm(ch1, ch2, m, n, p, one, %val(A), m,
+         %val(B), p, zero, %val(C), m)

return
end
```

Link to the BLAS library, which contains the `dgemm` function.

```
blaslib = fullfile(matlabroot, 'extern', 'lib', computer('arch'), 'microsoft', ...
    'libmwblas.lib');
```

To build the file, type:

```
mex('-v', '-largeArrayDims', 'callldgemv.F', blaslib)
```

## Handling Complex Numbers in LAPACK and BLAS Functions

MATLAB stores complex numbers differently than Fortran. MATLAB stores the real and imaginary parts of a complex number in separate, equal length vectors, `pr` and `pi`. Fortran stores the same complex number in one location with the real and imaginary parts interleaved.

As a result, complex variables exchanged between MATLAB and a Fortran function are incompatible. Use the conversion routines, `mat2fort` and `fort2mat`, that change the storage format of complex numbers to address this incompatibility.

- `mat2fort` — Convert MATLAB complex matrix to Fortran complex storage.
- `fort2mat` — Convert Fortran complex storage to MATLAB real and imaginary parts.

The `fort.c` and `fort.h` files provide routines for conversion between MATLAB and Fortran complex data structures. These files define the `mat2fort` and `fort2mat` routines.

To use these routines:

- 1 Include the `fort.h` header file in your source file, using the statement `#include "fort.h"`.
- 2 Link the `fort.c` file with your program. Specify the full path, `matlabroot/extern/examples/refbook` for `fort.c` in the build command.
- 3 To indicate the header file, use the `-Ipathname` switch. Specify the full path, `matlabroot/extern/examples/refbook` for `fort.h` in the build command.
- 4 When you specify the full path, replace the term `matlabroot` with the actual folder name.

### Handling Complex Number Input Values

It is unnecessary to copy arguments for functions that use complex number input values. The `mat2fort` conversion routine creates a copy of the arguments for you. For information, see “Preserving Input Values from Modification” on page 4-28.

## Handling Complex Number Output Arguments

For complex variables returned by a Fortran function, do the following:

- 1 When allocating storage for the variable, allocate a real variable with twice as much space as you would for a variable of the same size. Do this because the returned variable uses the Fortran format, which takes twice the space. See the allocation of `zout` in the example.
- 2 To make the variable compatible with MATLAB, use the `fort2mat` function.

### Example — Passing Complex Variables

This example shows how to call a function, passing complex `prhs[0]` as input and receiving complex `plhs[0]` as output. Temporary variables `zin` and `zout` contain the input and output values in Fortran format. To see the example, open the file in the MATLAB Editor. To create the MEX file, copy the source file to a writable folder.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'matrixDivideComplex.c'), '.');
```

To build the file on a Windows platform, type:

```
lapacklib = fullfile(matlabroot, 'extern', 'lib', computer('arch'), 'microsoft', ...  
    'libmwlpack.lib');  
fortfile = fullfile(matlabroot, 'extern', 'examples', 'refbook', 'fort.c');  
fortheadir = fullfile(matlabroot, 'extern', 'examples', 'refbook');  
mex('-v', '-largeArrayDims', ['-I' fortheadir], ...  
    'matrixDivideComplex.c', fortfile, lapacklib)
```

To build on a UNIX platform, type:

```
fortfile = fullfile(matlabroot, 'extern', 'examples', 'refbook', 'fort.c');  
fortheadir = fullfile(matlabroot, 'extern', 'examples', 'refbook');  
mex('-v', '-largeArrayDims', ['-I' fortheadir], ...  
    'matrixDivideComplex.c', fortfile, '-lmwlapack')
```

To test:

```
Areal = [1 2; 3 4];  
Aimag = [1 1; 0 0];  
Breal = [5; 6];  
Bimag = [0; 0];  
Acomplex = complex(Areal,Aimag);  
Bcomplex = complex(Breal,Bimag);  
X = matrixDivideComplex(Acomplex,Bcomplex)
```

```
X =
  -4.4000 + 0.8000i
   4.8000 - 0.6000i
```

### Example — Handling Fortran Complex Return Type

Some level 1 BLAS functions (for example, `zdotu` and `zdotc`) return a **double complex** type, which the C language does not support. The following C MEX file, `dotProductComplex.c`, shows how to handle the Fortran complex return type for function `zdotu`. To see the example, open the file in the MATLAB Editor.

The calling syntax for a C program calling a Fortran function that returns a value in an output argument is platform-dependent. On the Windows and Mac platforms, pass the return value as the first input argument. MATLAB provides a macro, `FORTRAN_COMPLEX_FUNCTIONS_RETURN_VOID`, to handle these differences.

The `dotProductComplex` example computes the dot product  $X$  of each element of two complex vectors  $A$  and  $B$ . The calling syntax is:

```
X = dotProductComplex(A,B)
```

where  $A$  and  $B$  are complex vectors of the same size and  $X$  is a complex scalar.

For example, to build the MEX file on a Windows platform, type:

```
blaslib = fullfile(matlabroot, 'extern', 'lib', computer('arch'), 'microsoft', ...
    'libmwblas.lib');
fortfile = fullfile(matlabroot, 'extern', 'examples', 'refbook', 'fort.c');
fortheaderdir = fullfile(matlabroot, 'extern', 'examples', 'refbook');
mex('-v', '-largeArrayDims', ['-I' fortheaderdir], ...
    'dotProductComplex.c', fortfile, blaslib)
```

To test, type;

```
a1 = [1+2i; 2+3i];
b1 = [-1+2i; -1+3i];
X = dotProductComplex(a1,b1)
```

```
X =
  -16.0000 + 3.0000i
```

### Example — Symmetric Indefinite Factorization Using LAPACK

The example `utdu_slv.c` calls LAPACK functions `zhesvx` and `dsysvx`. To see the example, open the file in the MATLAB Editor. To create the MEX file, copy the source file to a writable folder.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'utdu_slv.c'), '.')
```

To build the file on Windows, type:

```
lapacklib = fullfile(matlabroot, 'extern', 'lib', computer('arch'), 'microsoft', ...  
    'libmwlpack.lib');  
forheaderdir = fullfile(matlabroot, 'extern', 'examples', 'refbook');  
mex('-v', '-largeArrayDims', ['-I' forheaderdir], 'utdu_slv.c', fortfile, lapacklib)
```

To build on a UNIX platform, type:

```
mex -v -largeArrayDims utdu_slv.c -lmwlapack
```

## Modifying the Function Name on UNIX Systems

Add an underscore character following the function name when calling LAPACK or BLAS functions on a UNIX system. For example, to call `dgemm`, use:

```
dgemm_(arg1, arg2, ..., argn);
```

Or add these lines to your source code:

```
#if !defined(_WIN32)  
#define dgemm dgemm_  
#endif
```

## Upgrade MEX Files to Use 64-Bit API

### In this section...

“MATLAB Support for 64-Bit Indexing” on page 4-35

“MEX Uses 32-Bit API by Default” on page 4-35

“What If I Do Not Upgrade?” on page 4-37

“How to Upgrade MEX-Files to Use the 64-Bit API” on page 4-37

### MATLAB Support for 64-Bit Indexing

MATLAB Version 7.3 (R2006b) added support for 64-bit indexing. With 64-bit indexing, you can create variables with up to  $2^{48}-1$  elements on 64-bit platforms. Before Version 7.3, the C/C++ and Fortran API Reference library functions used `int` in C/C++ and `INTEGER*4` in Fortran to represent array dimensions. These types limit the size of an array to 32-bit integers. Simply building and running MEX-files on a 64-bit platform does not guarantee you access to the additional address space. You must update your MEX source code to take advantage of this functionality.

The following changes to the MX Matrix Library support 64-bit indexing:

- New types, `mwSize` and `mwIndex`, enabling large-sized data.
- Updated MX Matrix Library functions use `mwSize` and `mwIndex` types for inputs and outputs. These functions are called the *64-bit API* or the large-array-handling API.
- New `-largeArrayDims` flag for `mex` build command enabling use of the 64-bit API.

To help transition your MEX-files to the 64-bit API, MATLAB maintains an interface, or *compatibility layer*. To build MEX-files with this interface, use the `-compatibleArrayDims` flag.

---

**Note:** Only variables representing array size or index value require the `mwSize` or `mwIndex` types. The C-language `int` data type is valid for variables representing, for example, the number of fields or arrays.

---

### MEX Uses 32-Bit API by Default

The `mex` command uses the `-compatibleArrayDims` flag (32-bit API) by default. In a future version of MATLAB, the `mex` command will change to use the large-array-

handling API. Then, the `-largeArrayDims` option will be the default. This topic describes how to upgrade your MEX-files now in preparation for that transition.

### Can I Run Existing Binary MEX-Files?

You can run existing binary MEX-files without upgrading the files for use with the 64-bit API. However, unrelated incompatibilities that prevent execution of an existing MEX-file can occur. If your MEX-file does not execute properly, review the MEX Compatibility Considerations topics in the Release Notes for this release. To find MEX topics, check the External Interfaces section of the Compatibility Summary for MATLAB release notes table for each relevant version.

### Must I Update Source MEX-Files on 64-Bit Platforms?

If you build MEX-files on 64-bit platforms or write platform-independent applications, you must upgrade your MEX-files when the default changes. To *upgrade*, review your source code, make appropriate changes, and rebuild using the `mex` command.

Previous versions of the External Interfaces Release Notes provide instructions for updating your MEX-files. What action you take now depends on whether your MEX-files currently use the 64-bit API. The following table helps you identify your next actions.

State of Your Source Code	Next Action
I do not plan to update my code.	You have chosen to opt out and you must build using the <code>-compatibleArrayDims</code> flag.
I want to update my code. Where do I start?	See “How to Upgrade MEX-Files to Use the 64-Bit API” on page 4-37.
I use MEX-files, but do not have access to the source code.	Ask the owner of the source code to follow the steps in “How to Upgrade MEX-Files to Use the 64-Bit API” on page 4-37.
I use third-party libraries.	Ask the vendor if the libraries support 64-bit indexing. If not, you cannot use these libraries to create 64-bit MEX-files. Build your MEX-file using the <code>-compatibleArrayDims</code> flag.  If the libraries support 64-bit indexing, review your source code, following the steps



State of Your Source Code	Next Action
	in “How to Upgrade MEX-Files to Use the 64-Bit API” on page 4-37, and then test.
I updated my code in a previous release.	Review your source code, following the steps in “How to Upgrade MEX-Files to Use the 64-Bit API” on page 4-37, and then test.

### Must I Update Source MEX-Files on 32-Bit Platforms?

There are no changes to building 32-bit MEX-files. However, in a future version of MATLAB, the compatibility layer, with the `-compatibleArrayDims` flag, might be unsupported and you then would need to upgrade your MEX-files.

If you build MEX-files exclusively on 32-bit platforms, but want to write platform-independent code, you still can upgrade your code. If possible, build on a 64-bit system to validate your changes.

### What If I Do Not Upgrade?

On 32-bit platforms, you do not need to make any changes to build MEX-files.

On 64-bit platforms, you can build MEX-files by using the `-compatibleArrayDims` flag.

On 64-bit platforms, if you do not update your source files and you build without the `-compatibleArrayDims` flag, the results are unpredictable. One or more of the following could occur:

- Increased compiler warnings and/or errors from your native compiler
- Run-time errors
- Wrong answers

### How to Upgrade MEX-Files to Use the 64-Bit API

To review and update MEX-file source code, use the following checklist.

- 1 Prepare your code before editing — see “Back Up Files and Create Tests” on page 4-38.

**2** Iteratively change and test code.

Before building your MEX-files with the 64-bit API, refactor your existing code by checking for the following conditions:

- a** “Update Variables” on page 4-39.
- b** “Replace Unsupported Functions” on page 4-41.
- c** If necessary, “Update Fortran Source Code” on page 4-43.

After each change, build and test your code:

- Build with the 32-bit API. For example, to build `myMexFile.c`, type:  

```
mex -compatibleArrayDims myMexFile.c
```
- Test after each refactoring — see “Test, Debug, and Resolve Differences After Each Refactoring Iteration” on page 4-41.

**3** Compile using the 64-bit API. To build `myMexFile.c`, type:

```
mex -largeArrayDims myMexFile.c
```

- 4** Resolve failures and warnings — see “Resolve `-largeArrayDims` Build Failures and Warnings” on page 4-42.
- 5** Compare Results — see “Execute 64-Bit MEX-File and Compare Results with 32-Bit Version” on page 4-42.
- 6** Check memory — see “Experiment with Large Arrays” on page 4-42.

The following procedures use C/C++ terminology and example code. Fortran MEX-files share the same issues, with more tasks described in “Update Fortran Source Code” on page 4-43.

**Back Up Files and Create Tests**

Before adapting your code to handle large arrays, verify the MEX-file works with the traditional 32-bit array dimensions. At a minimum, build a list of expected inputs and outputs, or create a full test suite. To compare the results with the upgraded source code, use these tests. The results should be identical.

Back up all source, binary, and test files.

## Update Variables

To handle large arrays, convert variables containing array indices or sizes to use the `mwSize` and `mwIndex` types instead of the 32-bit `int` type. Review your code to see if it contains the following types of variables:

- Variables used directly by the MX Matrix Library functions — see “Update Arguments Used to Call Functions in the 64-Bit API” on page 4-39.
- Intermediate variables — see “Update Variables Used for Array Indices and Sizes” on page 4-40.
- Variables used as both size/index values and as 32-bit integers — see “Analyze Other Variables” on page 4-40.

## Update Arguments Used to Call Functions in the 64-Bit API

Identify the 64-bit API functions in your code that use the `mwSize` / `mwIndex` types. For the list of functions, see “Using the 64-Bit API” on page 5-62. Search for the variables that you use to call the functions. Check the function signature, shown under the **Syntax** heading on the function reference documentation. The signature identifies the variables that take `mwSize` / `mwIndex` values as input or output values. Change your variables to use the correct type.

For example, suppose that your code uses the `mxCreateDoubleMatrix` function, as shown in the following statements:

```
int nrows,ncolumns;
...
y_out = mxCreateDoubleMatrix(nrows, ncolumns, mxREAL);
```

To see the function signature, type:

```
doc mxCreateDoubleMatrix
```

The signature is:

```
mxArray *mxCreateDoubleMatrix(mwSize m, mwSize n,      mxComplexity ComplexFlag)
```

The type for input arguments `m` and `n` is `mwSize`. Change your code as shown in the table.

Replace:	With:
<code>int nrows,ncolumns;</code>	<code>mwSize nrows,ncolumns;</code>

### Update Variables Used for Array Indices and Sizes

If your code uses intermediate variables to calculate size and index values, use `mwSize` / `mwIndex` for these variables. For example, the following code declares the inputs to `mxCreateDoubleMatrix` as type `mwSize`:

```
mwSize nrows,ncolumns; /* inputs to mxCreateDoubleMatrix */
int numDataPoints;
nrows = 3;
numDataPoints = nrows * 2;
ncolumns = numDataPoints + 1;
...
y_out = mxCreateDoubleMatrix(nrows, ncolumns, mxREAL);
```

This example uses the intermediate variable, *numDataPoints* (of type `int`), to calculate the value of *ncolumns*. If you copy a 64-bit value from *nrows* into the 32-bit variable, *numDataPoints*, the resulting value truncates. Your MEX-file could crash or produce incorrect results. Use type `mwSize` for *numDataPoints*, as shown in the following table.

Replace:	With:
<code>int numDataPoints;</code>	<code>mwSize numDataPoints;</code>

### Analyze Other Variables

You do not need to change every integer variable in your code. For example, field numbers in structures and status codes are of type `int`. However, you need to identify variables used for multiple purposes and, if necessary, replace them with multiple variables.

The following example creates a matrix, *myNumeric*, and a structure, *myStruct*, based on the number of sensors. The code uses one variable, *numSensors*, for both the size of the array and the number of fields in the structure.

```
mxAarray *myNumeric, *myStruct;
int numSensors;
mwSize m, n;
char **fieldnames;
...
myNumeric = mxCreateDoubleMatrix(numSensors, n, mxREAL);
myStruct = mxCreateStructMatrix(m, n, numSensors, fieldnames);
```

The function signatures for `mxCreateDoubleMatrix` and `mxCreateStructMatrix` are:

```
mxAarray *mxCreateDoubleMatrix(mwSize m, mwSize n,
```

```

    mxComplexity ComplexFlag)
mxArray *mxCreateStructMatrix(mwSize m, mwSize n,
    int nfields, const char **fieldnames);

```

For the `mxCreateDoubleMatrix` function, your code uses `numSensors` for the variable `m`. The type for `m` is `mwSize`. For the `mxCreateStructMatrix` function, your code uses `numSensors` for the variable `nfields`. The type for `nfields` is `int`. Replace `numSensors` with two new variables to handle both functions, as shown in the following table.

Replace:	With:
<pre>int numSensors;</pre>	<pre>/* create 2 variables */ /* of different types */ mwSize numSensorSize; int numSensorFields;</pre>
<pre>myNumeric =     mxCreateDoubleMatrix(         numSensors,         n, mxREAL);</pre>	<pre>/* use mwSize variable */ /* numSensorSize */ myNumeric =     mxCreateDoubleMatrix(         numSensorSize,         n, mxREAL);</pre>
<pre>myStruct =     mxCreateStructMatrix(         m, n,         numSensors,         fieldnames);</pre>	<pre>/* use int variable */ /* numSensorFields */ myStruct =     mxCreateStructMatrix(         m, n,         numSensorFields,         fieldnames);</pre>

## Replace Unsupported Functions

While updating older MEX-files, you could find calls to unsupported functions, such as `mxCreateFull`, `mxGetName`, or `mxIsString`. MATLAB removed support for these functions in Version 7.1 (R14SP3). You cannot use unsupported functions with 64-bit array dimensions. For the list of unsupported functions and the recommended replacements, see “Obsolete Functions No Longer Documented”.

Update your code to use an equivalent function, if available. For example, use `mxCreateDoubleMatrix` instead of `mxCreateFull`.

## Test, Debug, and Resolve Differences After Each Refactoring Iteration

To build `myMexFile.c` with the 32-bit API, type:

```
mex -compatibleArrayDims myMexFile.c
```

Use the tests you created at the beginning of this process to compare the results of your updated MEX-file with your original binary file. Both MEX-files should return identical results. If not, debug and resolve any differences. Differences are easier to resolve now than when you build using the 64-bit API.

### **Resolve -largeArrayDims Build Failures and Warnings**

After reviewing and updating your code, compile your MEX-file using the large array handling API. To build `myMexFile.c` with the 64-bit API, type:

```
mex -largeArrayDims myMexFile.c
```

Since the `mwSize / mwIndex` types are MATLAB types, your compiler sometimes refers to them as `size_t`, `unsigned_int64`, or by other similar names.

Most build problems are related to type mismatches between 32- and 64-bit types. Refer to <http://www.mathworks.com/matlabcentral/answers/99144-how-do-i-update-mex-files-to-use-the-large-array-handling-api-largearraydims>, Step 5 to identify common build problems for specific compilers, and possible solutions.

### **Execute 64-Bit MEX-File and Compare Results with 32-Bit Version**

Compare the results of running your MEX-file compiled with the 64-bit API with the results from your original binary. If there are any differences or failures, use a debugger to investigate the cause. For information on the capabilities of your debugger, refer to your compiler documentation.

Refer to <http://www.mathworks.com/matlabcentral/answers/99144-how-do-i-update-mex-files-to-use-the-large-array-handling-api-largearraydims>, Step 6 to identify issues you might encounter when running your MEX-files, and possible solutions.

After you resolve any issues and upgrade your MEX-file, it replicates the functionality of your original code while using the large array handling API.

### **Experiment with Large Arrays**

If you have access to a machine with large amounts of memory, you can experiment with large arrays. An array of double-precision floating-point numbers (the default in MATLAB) with  $2^{32}$  elements takes approximately 32 GB of memory.

For an example that demonstrates the use of large arrays, see the `arraySize.c` MEX-file in “Handling Large `mxArrays`” on page 5-62.

### Update Fortran Source Code

All of the previous information applies to Fortran, as well as C/C++. Fortran uses similar API signatures, identical `mwSize` / `mwIndex` types, and similar compilers and debuggers. To make your Fortran source code 64-bit compatible, perform these additional tasks:

- “Use Fortran API Header File” on page 4-43
- “Declare Fortran Pointers” on page 4-43
- “Require Fortran Type Declarations” on page 4-43
- “Use Variables in Function Calls” on page 4-44
- “Manage Reduced Fortran Compiler Warnings” on page 4-45

### Use Fortran API Header File

To make your Fortran MEX-file compatible with the 64-bit API, use the `fintrf.h` header file in your Fortran source files. Name your source files with an uppercase `.F` file extension. For more information about these requirements, see “Components of Fortran MEX File” on page 6-2.

### Declare Fortran Pointers

Pointers are 32- or 64-bit addresses, based on machine type. This requirement is not directly tied to array dimensions, but you could encounter problems when moving 32-bit code to 64-bit machines as part of this conversion.

For more information, see “Preprocessor Macros” on page 6-5 and `mwPointer`.

The C/C++ compiler automatically handles pointer size. In Fortran, MATLAB uses the `mwPointer` type to handle this difference. For example, `mxCreateDoubleMatrix` returns an `mwPointer`:

```
mwPointer mxCreateDoubleMatrix(m, n, ComplexFlag)
mwSize m, n
integer*4 ComplexFlag
```

### Require Fortran Type Declarations

Fortran uses implicit type definitions. This means undeclared variables starting with letters `I` through `N` are implicitly declared type `INTEGER`. Variable names starting with

other letters are implicitly declared type `REAL*4`. Using the implicit `INTEGER` type could work for 32-bit indices, but is not safe for large array dimension MEX-files. To force you to declare all variables, add the `IMPLICIT NONE` statement to your Fortran subroutines. For example:

```
subroutine mexFunction(nlhs, plhs, nrhs, prhs)
implicit none
```

This statement helps identify 32-bit integers in your code that do not have explicit type declarations. Then, you can declare them as `INTEGER*4` or `mwSize / mwIndex`, as appropriate. For more information on `IMPLICIT NONE`, refer to your Fortran compiler documentation.

### Use Variables in Function Calls

If you use a number as an argument to a function, your Fortran compiler could assign the argument an incorrect type. On a 64-bit platform, an incorrect type can produce **Out of Memory** errors, segmentation violations, or incorrect results. For example, definitions for the argument types for the `mxCreateDoubleMatrix` function are:

```
mwPointer mxCreateDoubleMatrix(m, n, ComplexFlag)
mwSize m, n
integer*4 ComplexFlag
```

Suppose that you have a C/C++ MEX-file with the following statement:

```
myArray = mxCreateDoubleMatrix(2, 3, mxREAL);
```

Most C/C++ compilers interpret the number `2` as a 64-bit value. Some Fortran compilers cannot detect this requirement, and supply a 32-bit value. For example, an equivalent Fortran statement is:

```
myArray = mxCreateDoubleMatrix(2, 3, 0)
```

The compiler interprets the value of the `ComplexFlag` argument `0` correctly as type `INTEGER*4`. However, the compiler could interpret the argument `2` as a 32-bit value, even though the argument `m` is declared type `mwSize`.

A compiler-independent solution to this problem is to declare and use an `mwSize / mwIndex` variable instead of a literal value. For example, the following statements unambiguously call the `mxCreateDoubleMatrix` function in Fortran:

```
mwSize nrows, ncols
INTEGER*4 flag
```



```
nrows = 2  
ncols = 3  
flag = 0  
myArray = mxCreateDoubleMatrix(nrows, ncols, flag)
```

### **Manage Reduced Fortran Compiler Warnings**

Some Fortran compilers cannot detect as many type mismatches as similar C/C++ compilers. This inability can complicate the step “Resolve -largeArrayDims Build Failures and Warnings” on page 4-42 by leaving more issues to find with your debugger in the step “Execute 64-Bit MEX-File and Compare Results with 32-Bit Version” on page 4-42.

## Upgrade MEX Files to Use Graphics Objects

MATLAB Version 8.4 (R2014b) changes the data type of handles to graphics objects from `double` to *object*.

Before Version 8.4, MEX files used the C/C++ and Fortran API Reference library functions `mexGet` and `mexSet`, which declare the input handle argument as type `double`. If your MEX function uses `mexGet` or `mexSet`, MATLAB displays the following “Deprecated MEX function” error.

Error using mex

Deprecated MEX function mexGet|mxSet was called. Either update the source code to use `mxGetProperty|mxSetProperty`, OR rerun MEX with the `-DMEX_DOUBLE_HANDLE` added to the command line to enter compatibility mode.

To upgrade your MEX file, consider one or more of the following actions.

In this section...
“Replace <code>mexGet</code> and <code>mexSet</code> Functions” on page 4-46
“mex Automatically Converts Handle Type” on page 4-49
“I Want to Rebuild MEX Source Code Files” on page 4-49
“I Do Not Have MEX Source Code File” on page 4-49

### Replace `mexGet` and `mexSet` Functions

To upgrade a MEX file to use a graphics object, replace calls to `mexGet` with `mxGetProperty` and calls to `mexSet` with `mxSetProperty`. The following program listings show an example of a before and after source MEX file.

The following code uses `mexCallMATLAB` to create a plot, which returns the graphics handle in variable `plhs[0]`. To change the line color, the example uses `mxGetScalar` to convert the handle to a `double`, then passes it to `mexGet` and `mexSet`.

```
#include "mex.h"
#define RED 0
#define GREEN 1
#define BLUE 2

void fill_array(double *x)
```

```

{
    int i = 0;
    for(i = 0 ; i < 4 ; i++)
    {
        x[i] = i+1;
    }
}

void mexFunction(int nlhs, mxArray *plhs[], int nrhs, const mxArray *prhs[])
{
    mxArray *color;
    int ret;
    double handle;
    mxArray *copycolor;
    double *acolor;

    mxArray *data = mxCreateDoubleMatrix(1,4,mxREAL);
    fill_array(mxGetPr(data));

    ret = mexCallMATLAB(1,&plhs[0],1,&data,"plot");
    if(!ret)
    {
        handle = mxGetScalar(plhs[0]);
        color = mexGet(handle,"Color");
        copycolor = mxDuplicateArray(color);
        acolor = mxGetPr(copycolor);
        acolor[RED] = (1 + acolor[RED]) /2;
        acolor[GREEN] = acolor[GREEN]/2;
        acolor[BLUE] = acolor[BLUE]/2;

        mexSet(handle,"Color",copycolor);
        mxSetProperty(plhs[0],0,"Color",copycolor);
    }
}

```

When you build this MEX file, MATLAB displays the “Deprecated MEX function” error.

To change the source file, make the following edits. This code uses the variable `plhs[0]` in `mxGetProperty` to get the `Color` property directly. There is no need to create an intermediate `handle` variable.

```

#include "mex.h"
#define RED 0
#define GREEN 1

```

```
#define BLUE 2

void fill_array(double *x)
{
    int i = 0;
    for(i = 0 ; i < 4 ; i++)
    {
        x[i] = i+1;
    }
}

void mexFunction(int nlhs, mxArray *plhs[], int nrhs, const mxArray *prhs[])
{
    mxArray *color;
    int ret;

    mxArray *copycolor;
    double *acolor;

    mxArray *data = mxCreateDoubleMatrix(1,4,mxREAL);
    fill_array(mxGetPr(data));

    ret = mexCallMATLAB(1,&plhs[0],1,&data,"plot");
    if(!ret)
    {
        color = mxGetProperty(plhs[0],0,"Color");
        copycolor = mxDuplicateArray(color);
        acolor = mxGetPr(copycolor);
        acolor[RED] = (1 + acolor[RED]) /2;
        acolor[GREEN] = acolor[GREEN]/2;
        acolor[BLUE] = acolor[BLUE]/2;

        mxSetProperty(plhs[0],0,"Color",copycolor);
    }
}
```

To build this MEX file, type:

```
mex mymex.c
```

```
Building with 'Microsoft Visual C++ 2012 (C)'.
MEX completed successfully.
```

Alternatively, you can build the original source file by following the steps in “I Want to Rebuild MEX Source Code Files” on page 4-49.

## mex Automatically Converts Handle Type

If your MEX function uses the `mexCallMATLAB` or `mexGetVariable` functions to get a graphics handle and to pass the handle to the `mexGet` and `mexSet` APIs, then MATLAB automatically detects that behavior and your MEX function continues to execute correctly. You know that your MEX function uses this pattern if the function executes without error.

If you rebuild this MEX file in MATLAB R2014b or later, MATLAB displays the “Deprecated MEX function” error. To rebuild the file, follow the instructions in either “Replace `mexGet` and `mexSet` Functions” on page 4-46 or “I Want to Rebuild MEX Source Code Files” on page 4-49.

## I Want to Rebuild MEX Source Code Files

If you rebuild your MEX source files in MATLAB R2014b or later, MATLAB displays the “Deprecated MEX function” error.

You might be able to use the `mex` command compatibility flag, `-DMEX_DOUBLE_HANDLE`, to build the MEX file to work with graphics objects. If the MEX function calls a function that returns a graphics handle using the `mexCallMATLAB` or `mexGetVariable` functions, MATLAB automatically detects and converts the handle type. To build the source file, `mymex.c`, type:

```
mex -DMEX_DOUBLE_HANDLE mymex.c
```

If you pass a graphics handle to a MEX function, convert the handle to `double` before calling the function. For more information, see “I Do Not Have MEX Source Code File” on page 4-49.

## I Do Not Have MEX Source Code File

If you get a runtime error and you do not have the source code, you might be able to use the following workaround. Use this workaround only for MEX functions that take a graphics handle as an input argument.

Before you pass a graphics handle to the MEX function, first convert the handle to a `double`. For example, if you call MEX function, `mymex`:

```
Y = 1:10;  
h = plot(Y);
```

```
mymex(h)
```

add a statement to convert the handle `h` to double:

```
Y = 1:10;  
h = plot(Y);  
h = double(h);  
mymex(h)
```

### See Also

[mxGetProperty](#) | [mxSetProperty](#)

### More About

- “Graphics Object Handles”

## Platform Compatibility

If you obtain a binary MEX file from another source, be sure that the file was compiled for the same platform on which you want to run it. The file extension reflects the platform, as shown in the following table. To determine the extension for your platform, use the `mexext` function.

### MEX File Platform-Dependent Extension

Platform	Binary MEX File Extension
Linux (64-bit)	<code>mexa64</code>
Apple Mac (64-bit)	<code>mexmaci64</code>
Windows (64-bit)	<code>mexw64</code>

---

**Note:** It is not possible to run a 32-bit MEX file from within a 64-bit version of MATLAB.

---

### See Also

`mexext`

### More About

- “Version Compatibility” on page 4-57

## Invalid MEX File Error

If MATLAB cannot find all `.dll` files referenced by a MEX file, it cannot load the MEX file. MATLAB displays the following error message:

```
Invalid MEX-file <mexfilename>:  
The specified module could not be found.
```

where `mexfilename` is the module with the dependency error. This module cannot find its dependent libraries. To resolve this error, find the names of the dependent libraries, and determine if they are present on your system and on the system path.

To find library dependencies:

- On Windows systems, download the Dependency Walker utility from the website <http://www.dependencywalker.com/>.

- On Linux systems use:

```
ldd -d libname.so
```

- On Mac OS X systems use:

```
otool -L libname.dylib
```

For `.dll` files that the MEX file linked against when it was built, the `.dll` files must be on the system path or in the same folder as the MEX file.

MEX files might require additional libraries that are not linked to the MEX file. Failure to find one of these explicitly loaded libraries might not prevent a MEX file from loading, but prevents it from working correctly. The search path used to find these explicitly loaded libraries is controlled by the code that loads the libraries and might not include the folder that contains the MEX file. Consult the library documentation on proper installation locations.

Possible reasons for failure include:

- MATLAB version incompatibility
- Missing compiler runtime libraries. If your system does not have the same compiler that built the MEX file, see the Microsoft MSDN website for information about Visual C++ Redistributable Packages.
- Missing or incorrectly installed specialized runtime libraries. Contact your MEX file or library vendor.



## Run MEX File You Receive from Someone Else

To call a MEX file, put the file on your MATLAB path. Then type the name of the file, without the file extension.

If you have MEX file source code, see “Build MEX File” on page 4-17 for information about creating the executable function.

If you get runtime errors when you call a MEX file that you did not create, consider the following:

- “Platform Compatibility” on page 4-51
- “Version Compatibility” on page 4-57
- On Windows platforms, install the C++ compiler runtime libraries used to create the MEX file. This step is needed if you do not have the same compiler installed on your machine that was used to compile the MEX file.
- If the MEX file uses specialized runtime libraries, those libraries must be installed on your system.

If you write a MEX file, build it, and then execute it in the same MATLAB session, all of the dependent libraries are available, as expected. However, if you receive a MEX file from another MATLAB user, you might not have all of the dependent libraries.

A MEX file is a *dynamically linked* subroutine that the MATLAB interpreter loads and executes when you call the function. Dynamic linking means that when you call the function, the program looks for dependent libraries. MEX files use MATLAB runtime libraries and language-specific libraries. A MEX file might also use specialized runtime libraries. The code for these libraries is not included in the MEX file; the libraries must be present on your computer when you run the MEX file.

For troubleshooting library dependencies, see “Invalid MEX File Error” on page 4-52.

For information about how MATLAB finds a MEX file, see “Files and Folders that MATLAB Accesses”.

# MEX File Dependent Libraries

When you build a MEX file, MATLAB *dynamically links* your code with the following libraries:

- MATLAB runtime libraries, `libmex.dll` and `libmx.dll`. To avoid compatibility issues, run the MEX file with the same version of MATLAB that was used to create the MEX file. For more information, see “Version Compatibility” on page 4-57.
- Language-specific libraries, provided by the compiler. C-language MEX files built on Windows systems require Visual C++ runtime libraries.
- Other runtime libraries, which you specify in the build command.

Dynamic linking means that when you call the function, the program looks for these dependent libraries. The code for these libraries is not included in the MEX file. When you share a MEX file with another MATLAB user, these libraries must be present on the user’s computer.

## Document Build Information in the MEX File

This example shows how to document the `xtimesy` MEX file built on a Windows platform using a Microsoft Visual C++ compiler.

When you share a MEX file, your users need the following information about the configuration used to build the MEX file:

- MATLAB version.
- Build platform.
- Compiler.

Copy the source file to a folder on your MATLAB path.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'xtimesy.c'), '.')
```

Create a help file, `xtimesy.m`, and copy the header information from the source file.

```
% xtimesy.m Help file for XTIMESY MEX file
%
% XTIMESY Multiplies a scalar and a matrix
%   C = XTIMESY(b,A) multiplies scalar b with matrix A,
%   and returns the result in C
%
%   MEX File function.
```

Identify your MATLAB version.

```
v = ver('matlab');
v.Release
```

```
ans =
(R2012a)
```

Identify your platform.

```
archstr = computer('arch')
```

```
archstr =
win64
```

Identify the MEX file extension.

```
ext = mexext
```

```
ext =  
mexw64
```

Identify your C compiler.

```
cc = mex.getCompilerConfigurations('C', 'Selected');  
cc.Name
```

```
ans =  
Microsoft Visual C++ 2008 (C)
```

Add this information to the help file.

```
% xtimesy.m Help file for XTIMESY MEX file  
%  
% XTIMESY Multiplies a scalar and a matrix  
% C = XTIMESY(b,A) multiplies scalar b with matrix A,  
% and returns the result in C  
%  
% Created with:  
% MATLAB R2012a  
% Platform: win64  
% Microsoft Visual C++ 2008  
  
% MEX File function.
```

Provide your users with the following.

- `xtimesy.mexw64`
- `xtimesy.m`
- Instructions for downloading and installing the runtime library from the Microsoft Visual C++ 2008 Redistributable Package.
- If you build a MEX file with a third-party library, instructions for acquiring and installing the necessary files.

### Related Examples

- “Use Help Files with MEX Files” on page 4-6

## Version Compatibility

For best results, your version of MATLAB must be the same version that was used to create the MEX file.

MEX files use MATLAB runtime libraries. MEX files are usually backward compatible, which means you can run a MEX file that was created on an earlier version of MATLAB on later versions of MATLAB. If the MEX file generates errors, recompile the MEX file from the source code.

Sometimes a MEX file created on a newer version of MATLAB runs on an older version of MATLAB (forward compatibility), but this is not supported.

### More About

- “Platform Compatibility” on page 4-51

## Getting Help When MEX Fails

### In this section...

“Errors Finding Supported Compiler” on page 4-58

“Errors Building MEX Function” on page 4-58

“Preview mex Build Commands” on page 4-59

To help diagnose compiler set up and build errors, call `mex` with the verbose option, `-v`. For an example of the information `mex` provides, type the following commands from a writable folder:

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'timestwo.c'), '.', 'f')
mex -v timestwo.c
```

### Errors Finding Supported Compiler

In verbose mode, `mex` displays the steps used to find a supported compiler and to determine if it is properly installed. Each step begins with the following text:

```
... Looking for
```

If the compiler is not configured properly, these messages show you the expected values for specific files, paths, and variables in the configuration.

If the compiler is found, `mex` displays a message similar to:

```
Building with 'Microsoft Visual C++ 2012 (C)'.
```

### Errors Building MEX Function

After locating the installed compiler, indicated by the “Building with” message, verbose mode displays the compile and link commands `mex` passes to the build tools. For example, the compile command on Windows platforms might be similar to the following:

```
cl /c /GR /W3 /EHs /nologo /MD /DMX_COMPAT_32
/D_CRT_SECURE_NO_DEPRECATED /D_SCL_SECURE_NO_DEPRECATED /D_SECURE_SCL=0 /DMATLAB_MEX_FI
-I"matlabroot\extern\include" -I"matlabroot\simulink\include"
/O2 /Oy- /DNDEBUG C:\work\mex\timestwo.c /FoC:\work\timestwo.obj
timestwo.c
```

`mex` displays error messages from the compiler build tools. For information about errors and warnings, see your compiler or language reference documentation.

If you have experience with program development and want to modify a command parameter, use the `mex varname=varvalue` option.

## Preview mex Build Commands

To display the build command details without executing the commands, type:

```
mex -n timestwo.c
```

## See Also

`mex`

## Compiling MEX File Fails

### Build Example Files

Can you compile and run the `timestwo.c` or `timestwo.f` example files? See “Build MEX File” on page 4-17 or “Build Fortran MEX File” on page 6-13.

### Use Supported Compiler

Are you using a supported compiler? For an up-to-date list of supported compilers, see the Supported and Compatible Compilers website.

### File Not Found on Windows

The `mex` command cannot find files located in folder names that contain non-ASCII characters.

### Linux gcc -fPIC Errors

If you link a static library with a MEX file, which is a shared library, you might get an error message containing the text `recompile with -fPIC`. Try compiling the static library with the `-fPIC` flag in order to create position independent code. For information about using the `gcc` compiler, see [www.gnu.org](http://www.gnu.org). For an up-to-date list of supported compilers, see the Supported and Compatible Compilers website.

### Compiler Errors in Fortran MEX Files

When you compile a Fortran MEX file using a free source form format, MATLAB displays an error message of the following form:

```
Illegal character in statement label field
```

`mex` supports the fixed source form. The difference between free and fixed source forms is explained in the Fortran Language Reference Manual Source Forms topic.

### Syntax Errors Compiling C/C++ MEX Files on UNIX

If MATLAB header files generate multiple syntax errors when you compile your code on UNIX systems, you might be using a non-ANSI C compiler.



The most common configuration problem creating C/C++ MEX files on UNIX systems involves using a non-ANSI C compiler, or failing to pass a compiler flag telling it to compile ANSI C code.

One way to know if you have this type of configuration problem is if the MATLAB header files generate multiple syntax errors when you compile your code. If necessary, obtain an ANSI C compiler.

### **Related Examples**

- “Build MEX File” on page 4-17
- “Build Fortran MEX File” on page 6-13

### **More About**

- “What You Need to Build MEX Files” on page 4-19

### **External Websites**

- Supported and Compatible Compilers
- Fortran Language Reference Manual

## Symbol mexFunction Unresolved or Not Defined

Attempting to compile a MEX function that does not include a gateway function generates errors about the `mexFunction` symbol. For example, using a C/C++ compiler, MATLAB displays information like:

```
LINK : error LNK2001: unresolved external symbol mexFunction
```

Using a Fortran compiler, MATLAB displays information like:

```
unresolved external symbol _MEXFUNCTION
```

On Mac OS X platforms, MATLAB displays information like:

```
Undefined symbols for architecture x86_64:  
"_mexfunction_", referenced from:  
-exported_symbol[s_list] command line option
```

### More About

- “Components of MEX File” on page 5-3

## MEX File Segmentation Fault

If a binary MEX file causes a segmentation violation or assertion, it means that the MEX file attempted to access protected, read-only, or unallocated memory.

These types of programming errors can be difficult to track down. Segmentation violations do not always occur at the same point as the logical errors that cause them. If a program writes data to an unintended section of memory, an error might not occur until the program reads and interprets the corrupted data. Therefore, a segmentation violation can occur after the MEX file finishes executing.

One cause of memory corruption is to pass a null pointer to a function. To check for this condition, add code in your MEX file to check for invalid arguments to MEX Library and MX Matrix Library API functions.

To troubleshoot problems of this nature, run MATLAB within a debugging environment.

### Related Examples

- “Debug on Microsoft Windows Platforms” on page 5-53
- “Debug on Mac Platforms” on page 5-57
- “Debug on Linux Platforms” on page 5-55
- “Debug Fortran Source MEX-Files” on page 6-31

## MEX File Generates Incorrect Results

If your program generates the wrong answers, consider the following.

- Check for errors in the computational logic.
- Check if the program reads from an uninitialized section of memory. For example, reading the 11th element of a 10-element vector yields unpredictable results.
- Check if the program overwrites valid data due to memory mishandling. For example, writing to the 15th element of a 10-element vector overwrites data in the adjacent variable in memory. This case can be handled in a similar manner as segmentation violations.

In all these cases, you can use `mexPrintf` to examine data values at intermediate stages. Alternatively, run MATLAB within a debugger.

### See Also

`mexPrintf`

### Related Examples

- “Debug on Microsoft Windows Platforms” on page 5-53
- “Debug on Mac Platforms” on page 5-57
- “Debug on Linux Platforms” on page 5-55
- “Debug Fortran Source MEX-Files” on page 6-31

### More About

- “MEX File Segmentation Fault” on page 4-63

## Memory Management Issues

### In this section...

“Overview” on page 4-65

“Improperly Destroying an mxArray” on page 4-66

“Incorrectly Constructing a Cell or Structure mxArray” on page 4-66

“Creating a Temporary mxArray with Improper Data” on page 4-67

“Creating Potential Memory Leaks” on page 4-68

“Improperly Destroying a Structure” on page 4-68

“Destroying Memory in a C++ Class Destructor” on page 4-69

### Overview

When a MEX file returns control to MATLAB, it returns the results of its computations in the output arguments—the mxArrays contained in the left-side arguments `plhs[ ]`. These arrays must have a temporary scope, so do not pass arrays created with the `mexMakeArrayPersistent` function in `plhs`. MATLAB destroys any mxArray created by the MEX file that is not in `plhs`. MATLAB also frees any memory that was allocated in the MEX file using the `mxMalloc`, `mxRealloc`, or `mxMalloc` functions.

In general, MathWorks® recommends that MEX-file functions destroy their own temporary arrays and free their own dynamically allocated memory. It is more efficient to perform this cleanup in the source MEX-file than to rely on the automatic mechanism. This approach is consistent with other MATLAB API applications (MAT-file applications, engine applications, and MATLAB Compiler generated applications, which do not have any automatic cleanup mechanism.)

However, do not destroy an mxArray in a source MEX file when it is:

- passed to the MEX file in the right-hand side list `prhs[ ]`
- returned in the left side list `plhs[ ]`
- returned by `mexGetVariablePtr`
- used to create a structure

This section describes situations specific to memory management. We recommend that you review code in your source MEX files to avoid using these functions in the

following situations. For more information, see “Memory Management” on page 5-66 in *Creating C/C++ Language MEX Files*. For guidance on memory issues, see “Strategies for Efficient Use of Memory”.

Potential memory management problems include:

## Improperly Destroying an mxArray

Do not use `mxFree` to destroy an mxArray.

### Example

In the following example, `mxFree` does not destroy the array object. This operation frees the structure header associated with the array, but MATLAB still operates as if the array object needs to be destroyed. Thus MATLAB tries to destroy the array object, and in the process, attempts to free its structure header again:

```
mxArray *temp = mxCreateDoubleMatrix(1,1,mxREAL);  
    ...  
mxFree(temp); /* INCORRECT */
```

### Solution

Call `mxDestroyArray` instead:

```
mxDestroyArray(temp); /* CORRECT */
```

## Incorrectly Constructing a Cell or Structure mxArray

Do not call `mxSetCell` or `mxSetField` variants with `prhs[ ]` as the member array.

### Example

In the following example, when the MEX file returns, MATLAB destroys the entire cell array. Since this includes the members of the cell, this implicitly destroys the MEX file's input arguments. This can cause several strange results, generally having to do with the corruption of the caller's workspace, if the right-hand side argument used is a temporary array (for example, a literal or the result of an expression):

```
myfunction('hello')
```

```

/* myfunction is the name of your MEX file and your code
/* contains the following: */

    mxArray *temp = mxCreateCellMatrix(1,1);
    ...
    mxSetCell(temp, 0, prhs[0]); /* INCORRECT */

```

### Solution

Make a copy of the right-hand side argument with `mxDuplicateArray` and use that copy as the argument to `mxSetCell` (or `mxSetField` variants). For example:

```

mxSetCell(temp, 0, mxDuplicateArray(prhs[0])); /* CORRECT */

```

## Creating a Temporary mxArray with Improper Data

Do not call `mxDestroyArray` on an `mxArray` whose data was not allocated by an API routine.

### Example

If you call `mxSetPr`, `mxSetPi`, `mxSetData`, or `mxSetImagData`, specifying memory that was not allocated by `mxMalloc`, `mxMalloc`, or `mxRealloc` as the intended data block (second argument), then when the MEX file returns, MATLAB attempts to free the pointers to real data and imaginary data (if any). Thus MATLAB attempts to free memory, in this example, from the program stack:

```

mxArray *temp = mxCreateDoubleMatrix(0,0,mxREAL);
double data[5] = {1,2,3,4,5};
...
mxSetM(temp,1); mxSetN(temp,5); mxSetPr(temp, data);
/* INCORRECT */

```

### Solution

Rather than use `mxSetPr` to set the data pointer, instead, create the `mxArray` with the right size and use `memcpy` to copy the stack data into the buffer returned by `mxGetPr`:

```

mxArray *temp = mxCreateDoubleMatrix(1,5,mxREAL);
double data[5] = {1,2,3,4,5};
...
memcpy(mxGetPr(temp), data, 5*sizeof(double)); /* CORRECT */

```

## Creating Potential Memory Leaks

Before Version 5.2, if you created an `mxArray` using one of the API creation routines and then you overwrote the pointer to the data using `mxSetPr`, MATLAB still freed the original memory. MATLAB no longer frees the memory.

For example:

```
pr = mxCalloc(5*5, sizeof(double));
... <load data into pr>
plhs[0] = mxCreateDoubleMatrix(5,5,mxREAL);
mxSetPr(plhs[0], pr); /* INCORRECT */
```

now leaks  $5*5*8$  bytes of memory, where 8 bytes is the size of a `double`.

You can avoid that memory leak by changing the code to:

```
plhs[0] = mxCreateDoubleMatrix(5,5,mxREAL);
pr = mxGetPr(plhs[0]);
... <load data into pr>
```

or alternatively:

```
pr = mxCalloc(5*5, sizeof(double));
... <load data into pr>
plhs[0] = mxCreateDoubleMatrix(5,5,mxREAL);
mxFree(mxGetPr(plhs[0]));
mxSetPr(plhs[0], pr);
```

The first solution is more efficient.

Similar memory leaks can also occur when using `mxSetPi`, `mxSetData`, `mxSetImagData`, `mxSetIr`, or `mxSetJc`. You can avoid memory leaks by changing the code as described in this section.

## Improperly Destroying a Structure

For a structure, you must call `mxDestroyArray` only on the structure, not on the field data arrays. A field in the structure points to the data in the array used by `mxSetField` or `mxSetFieldByNumber`. When `mxDestroyArray` destroys the structure, it attempts to traverse down through itself and free all other data, including the memory in the data arrays. If you call `mxDestroyArray` on each data array, the same memory is freed twice which can corrupt memory.



## Example

The following example creates three arrays: one structure array `aStruct` and two data arrays, `myDataOne` and `myDataTwo`. Field name `one` contains a pointer to the data in `myDataOne`, and field name `two` contains a pointer to the data in `myDataTwo`.

```
mxArray *myDataOne;
mxArray *myDataTwo;
mxArray *aStruct;
const char *fields[] = { "one", "two" };

myDataOne = mxCreateDoubleScalar(1.0);
myDataTwo = mxCreateDoubleScalar(2.0);

aStruct = mxCreateStructMatrix(1,1,2,fields);
mxSetField( aStruct, 0, "one", myDataOne );
mxSetField( aStruct, 1, "two", myDataTwo );
mxDestroyArray(myDataOne);
mxDestroyArray(myDataTwo);
mxDestroyArray(aStruct); /* tries to free myDataOne and myDataTwo */
```

## Solution

The command `mxDestroyArray(aStruct)` destroys the data in all three arrays:

```
...
aStruct = mxCreateStructMatrix(1,1,2,fields);
mxSetField( aStruct, 0, "one", myDataOne );
mxSetField( aStruct, 1, "two", myDataTwo );
mxDestroyArray(aStruct);
```

## Destroying Memory in a C++ Class Destructor

Do not use the `mxFree` or `mxDestroyArray` functions in a C++ destructor of a class used in a MEX-function. If the MEX-function throws an error, MATLAB cleans up MEX-file variables, as described in “Automatic Cleanup of Temporary Arrays” on page 5-66.

If an error occurs that causes the object to go out of scope, MATLAB calls the C++ destructor. Freeing memory directly in the destructor means both MATLAB and the destructor free the same memory, which can corrupt memory.

## See Also

`mxDestroyArray` | `mxFree`

## **More About**

- “Memory Management” on page 5-66
- “Strategies for Efficient Use of Memory”
- “Automatic Cleanup of Temporary Arrays” on page 5-66

# C/C++ MEX-Files

---

- “Components of MEX File” on page 5-3
- “MATLAB API Libraries” on page 5-6
- “User Messages” on page 5-8
- “Error Handling” on page 5-9
- “Data Flow in MEX Files” on page 5-10
- “Creating C++ MEX Files” on page 5-13
- “C++ Class in MEX Files” on page 5-15
- “Handle Files with C++” on page 5-16
- “Create C Source MEX File” on page 5-18
- “Table of MEX File Source Code Files” on page 5-24
- “Choose a C++ Compiler” on page 5-29
- “Set Up C/C++ Examples” on page 5-31
- “Pass Scalar Values” on page 5-32
- “Pass Strings” on page 5-35
- “Handling Strings in C/C++” on page 5-37
- “Pass Multiple Inputs or Outputs” on page 5-40
- “Pass Structures and Cell Arrays” on page 5-42
- “Create 2-D Cell Array” on page 5-43
- “Fill mxArray” on page 5-44
- “Prompt User for Input” on page 5-46
- “Handle Complex Data” on page 5-47
- “Handle 8-, 16-, and 32-Bit Data” on page 5-48
- “Manipulate Multidimensional Numerical Arrays” on page 5-49
- “Handle Sparse Arrays” on page 5-51
- “Call MATLAB Functions from C/C++ MEX Files” on page 5-52

- “Debug on Microsoft Windows Platforms” on page 5-53
- “Debug on Linux Platforms” on page 5-55
- “Debug on Mac Platforms” on page 5-57
- “Handling Large mxArray’s” on page 5-62
- “Memory Management” on page 5-66
- “Handling Large File I/O” on page 5-69
- “Install MinGW-w64 Compiler” on page 5-75
- “Troubleshooting and Limitations Compiling C/C++ MEX Files with MinGW-w64” on page 5-77

## Components of MEX File

### In this section...

“mexFunction Gateway Routine” on page 5-3

“Naming the MEX File” on page 5-3

“Required Parameters” on page 5-3

“Managing Input and Output Parameters” on page 5-4

“Validating Inputs” on page 5-4

“Computational Routine” on page 5-5

### mexFunction Gateway Routine

The *gateway routine* is the entry point to the MEX file. It is through this routine that MATLAB accesses the rest of the routines in your MEX files. The name of the gateway routine is `mexFunction`. It takes the place of the `main` function in your source code.

### Naming the MEX File

The name of the source file containing `mexFunction` is the name of your MEX file, and, hence, the name of the function you call in MATLAB.

The file extension of the binary MEX file is platform-dependent. You find the file extension using the `mexext` function, which returns the value for the current machine.

### Required Parameters

The signature for `mexFunction` is:

```
void mexFunction(  
    int nlhs, mxArray *plhs[],  
    int nrhs, const mxArray *prhs[])
```

Place this function after your computational routine and any other functions in your source file.

The following table describes the parameters for `mexFunction`.

Parameter	Description
<code>prhs</code>	Array of right-side input arguments.
<code>plhs</code>	Array of left-side output arguments.
<code>nrhs</code>	Number of right-side arguments, or the size of the <code>prhs</code> array.
<code>nlhs</code>	Number of left-side arguments, or the size of the <code>plhs</code> array.

Declare `prhs` and `plhs` as type `mxArray *`, which means they point to MATLAB arrays. They are vectors that contain pointers to the arguments of the MEX file. The keyword `const`, which modifies `prhs`, means that your MEX file does not modify the input arguments.

You can think of the name `prhs` as representing the “parameters, right-hand side,” that is, the input parameters. Likewise, `plhs` represents the “parameters, left-hand side,” or output parameters.

## Managing Input and Output Parameters

Input parameters (found in the `prhs` array) are read-only; do not modify them in your MEX file. Changing data in an input parameter can produce undesired side effects.

You also must take care when using an input parameter to create output data or any data used locally in your MEX file. To copy an input array into a locally defined variable, `myData`, call the `mxDuplicateArray` function to make a copy of the input array. For example:

```
mxArray *myData = mxCreateStructMatrix(1,1,nfields,fnames);  
mxSetField(myData,0,"myFieldName",mxDuplicateArray(prhs[0]));
```

For more information, see the troubleshooting topic “Incorrectly Constructing a Cell or Structure `mxArray`” on page 4-66.

## Validating Inputs

For a list of functions to validate inputs to your functions, see the Matrix Library category, “Validate Data”.

The `mxIsClass` function is a general-purpose way to test an `mxArray`. For example, suppose your second input argument (identified by `prhs[1]`) must be a full matrix of real numbers. To check this condition, use the following statements.

```
if(mxIsSparse(prhs[1]) ||
    mxIsComplex(prhs[1]) ||
    mxIsClass(prhs[1], "char")) {
    mexErrMsgTxt("input2 must be full matrix of real values.");
}
```

This example is not an exhaustive check. You can also test for structures, cell arrays, function handles, and MATLAB objects.

## Computational Routine

The *computational routine* contains the code for performing the computations you want implemented in the binary MEX file. Although not required, consider writing the gateway routine, `mexFunction`, to call a computational routine. Use the `mexFunction` code as a wrapper to validate input parameters and to convert them into the types required by the computational routine.

If you write separate gateway and computational routines, you can combine them into one source file or into separate files. If you use separate files, the file containing `mexFunction` must be the first source file listed in the `mex` command.

## See Also

`mexext` | `mexFunction` | `mxDuplicateArray` | `mxIsClass`

## More About

- “MATLAB API Libraries” on page 5-6

## MATLAB API Libraries

In this section...
“Matrix Library” on page 5-6
“MEX Library” on page 5-6
“Preprocessor Macros” on page 5-6

Use Matrix Library and the MEX Library functions in gateway and computational routines to interact with data in the MATLAB workspace. These libraries are part of the MATLAB C/C++ and Fortran API Reference library.

To use these functions, include the `mex` header, which declares the entry point and interface routines. Put this statement in your source file:

```
#include "mex.h"
```

### Matrix Library

Use Matrix Library functions to pass *mxArray*, the type MATLAB uses to store arrays, to and from MEX files. For examples using these functions, see *matlabroot/extern/examples/mx*.

### MEX Library

Use MEX Library functions to perform operations in the MATLAB environment. For examples using these functions, see *matlabroot/extern/examples/mex*.

Unlike MATLAB functions, MEX file functions do not have their own variable workspace. MEX file functions operate in the caller workspace. Use `mexEvalString` to evaluate the command in the caller workspace. Use the `mexGetVariable` and `mexPutVariable` functions to get and put variables into the caller workspace.

### Preprocessor Macros

The Matrix and MEX libraries use the MATLAB *preprocessor macros* `mwSize` and `mwIndex` for cross-platform flexibility. `mwSize` represents size values, such as array dimensions and number of elements. `mwIndex` represents index values, such as indices into arrays.



**See Also**

`mexEvalString` | `mexGetVariable` | `mexPutVariable` | `mwIndex` | `mwSize` | `mxArray`

**More About**

- “MATLAB Data” on page 4-7
- “MEX Library API”
- C/C++ Matrix Library

## User Messages

To print text in the MATLAB Command Window, use the `mexPrintf` function as you would a C/C++ `printf` function. To print error and warning information in the Command Window, use the `mexErrMsgIdAndTxt` and `mexWarnMsgIdAndTxt` functions.

For example, the following code snippet prints `prhs[0]`.

```
char *buf;
int buflen;

if (mxGetString(prhs[0], buf, buflen) == 0) {
    mexPrintf("The input string is: %s\n", buf);
}
```

### See Also

`mexErrMsgIdAndTxt` | `mexPrintf` | `mexWarnMsgIdAndTxt`

## Error Handling

The `mexErrMsgIdAndTxt` function prints error information and terminates your binary MEX file. The `mexWarnMsgIdAndTxt` function prints information, but does not terminate the MEX file.

```
char *buf;
int buflen;

if (mxIsChar(prhs[0])) {
    if (mxGetString(prhs[0], buf, buflen) == 0) {
        mexPrintf("The input string is: %s\n", buf);
    }
    else {
        mexErrMsgIdAndTxt("MyProg:ConvertString",
            "Could not convert string data.");
        // exit MEX file
    }
}
else {
    mexWarnMsgIdAndTxt("MyProg:InputString",
        "Input should be a string to print properly.");
}

// continue with processing
```

### See Also

[mexErrMsgIdAndTxt](#) | [mexWarnMsgIdAndTxt](#)

## Data Flow in MEX Files

### In this section...

“Showing Data Input and Output” on page 5-10

“Gateway Routine Data Flow Diagram” on page 5-11

### Showing Data Input and Output


Suppose your MEX-file `myFunction` has two input arguments and one output argument. The MATLAB syntax is `[X] = myFunction(Y, Z)`. To call `myFunction` from MATLAB, type:

```
X = myFunction(Y, Z);
```

The MATLAB interpreter calls `mexFunction`, the gateway routine to `myFunction`, with the following arguments:

```
nlhs = 1
```

```
nrhs = 2
```



Your input is `prhs`, a two-element array (`nrhs = 2`). The first element is a pointer to an `mxAarray` named `Y` and the second element is a pointer to an `mxAarray` named `Z`.

Your output is `plhs`, a one-element array (`nlhs = 1`) where the single element is a `null` pointer. The parameter `plhs` points at nothing because the output `X` is not created until the subroutine executes.

The gateway routine creates the output array and sets a pointer to it in `plhs[0]`. If the routine does not assign a value to `plhs[0]` but you assign an output value to the function when you call it, MATLAB generates an error.

---

**Note:** It is possible to return an output value even if `nlhs = 0`, which corresponds to returning the result in the `ans` variable.

---


## Gateway Routine Data Flow Diagram

The following MEX Cycle diagram shows how inputs enter a MEX-file, what functions the gateway routine performs, and how outputs return to MATLAB.

In this example, the syntax of the MEX-file `func` is `[C, D] = func(A,B)`. In the figure, a call to `func` tells MATLAB to pass variables `A` and `B` to your MEX-file. `C` and `D` are left unassigned.

The gateway routine, `func.c`, uses the `mxCreate*` functions to create the MATLAB arrays for your output arguments. It sets `plhs[0]` and `plhs[1]` to the pointers to the newly created MATLAB arrays. It uses the `mxGet*` functions to extract your data from your input arguments `prhs[0]` and `prhs[1]`. Finally, it calls your computational routine, passing the input and output data pointers as function parameters.

MATLAB assigns `plhs[0]` to `C` and `plhs[1]` to `D`.



## C/C++ MEX Cycle

## Related Examples

- “Create C Source MEX File” on page 5-18

## Creating C++ MEX Files

### In this section...

“Creating Your C++ Source File” on page 5-13

“Compiling and Linking” on page 5-13

“Memory Considerations for Class Destructors” on page 5-13

“Use mexPrintf to Print to MATLAB Command Window” on page 5-14

MEX files support all C++ language standards. This topic discusses specific C++ language issues to consider when creating and using MEX files.

Use the C syntax statements in the MATLAB API libraries in your C++ applications. You can also copy MATLAB C code examples into C++ applications. For example, see the `mexcpp.cpp` file that contains both C and C++ statements.

### Creating Your C++ Source File

The C++ source code for the examples provided by MATLAB use the `.cpp` file extension. The extension `.cpp` is unambiguous and recognized by C++ compilers. Other possible extensions include `.C`, `.cc`, and `.cxx`.

### Compiling and Linking

To build a C++ MEX file, type:

```
mex filename.cpp
```

where *filename* is the name of the source file.

You can run a C++ MEX file only on systems with the same version of MATLAB that the file was compiled on.

### Memory Considerations for Class Destructors

Do not use the `mxFree` or `mxDestroyArray` functions in a C++ destructor of a class used in a MEX-function. If the MEX-function throws an error, MATLAB cleans up MEX-file variables, as described in “Automatic Cleanup of Temporary Arrays” on page 5-66.

If an error occurs that causes the object to go out of scope, MATLAB calls the C++ destructor. Freeing memory directly in the destructor means both MATLAB and the destructor free the same memory, which can corrupt memory.

### **Use `mexPrintf` to Print to MATLAB Command Window**

Using `cout` or the C-language `printf` function does not work as expected in C++ MEX files. Use the `mexPrintf` function instead.

### **See Also**

`mexPrintf`

### **Related Examples**

- “C++ Class in MEX Files” on page 5-15
- “Handle Files with C++” on page 5-16
- `mexcpp.cpp`

### **More About**

- “Build MEX File” on page 4-17



## C++ Class in MEX Files

This example, `mexcpp.cpp`, shows how to use C++ code with your C language MEX file. It uses member functions, constructors, destructors, and the `iostream` include file.

To build this example, at the command prompt type:

```
mex mexcpp.cpp
```

The calling syntax is `mexcpp(num1, num2)`.

The routine defines a class, `myData`, with member functions `display` and `set_data`, and variables `v1` and `v2`. It constructs an object `d` of class `myData` and displays the initialized values of `v1` and `v2`. It then sets `v1` and `v2` to your input and displays the new values. Finally, the `delete` operator cleans up the object.

### Related Examples

- `mexcpp.cpp`

## Handle Files with C++

### In this section...

“C++ Example” on page 5-16

“C Example” on page 5-16

The `mexatexit.cpp` example shows C++ file handling features. Compare it with the C code example `mexatexit.c`, which uses the `mexAtExit` function.

### C++ Example

The C++ example uses a `fileresource` class to handle the file open and close functions. The MEX file calls the destructor for this class (which closes the data file). This example also prints a message on the screen when performing operations on the data file. However, in this case, the only C file operation performed is the write operation, `fprintf`.

To build the `mexatexit.cpp` MEX file, type:

```
mex mexatexit.cpp
```

Type:

```
z = 'for the C++ MEX-file';  
mexatexit(x)  
mexatexit(z)  
clear mexatexit
```

```
Writing data to file.
```

```
Writing data to file.
```

Display the contents of `matlab.data`.

```
type matlab.data
```

```
my input string  
for the C++ MEX-file
```

### C Example

The C code example registers the `mexAtExit` function to perform cleanup tasks (close the data file) when the MEX file clears. This example prints a message on the screen (using `mexPrintf`) when performing file operations `fopen`, `fprintf`, and `fclose`.

To build the MEX file, type:

```
mex mexatexit.c
```

Run the example.

```
x = 'my input string';  
mexatexit(x)
```

```
Opening file matlab.data.  
Writing data to file.
```

Clear the MEX file.

```
clear mexatexit
```

```
Closing file matlab.data.
```

Display the contents of `matlab.data`.

```
type matlab.data
```

```
my input string
```

## See Also

`mexAtExit`

## Related Examples

- `mexatexit.cpp`
- `mexatexit.c`

## Create C Source MEX File

This example shows how to write a MEX file to call a C function, `arrayProduct`, in MATLAB using a MATLAB matrix. You can use these same C statements in a C++ application.

`arrayProduct` multiplies a `1xn` matrix, `y`, by a scalar value, `x`, and returns the results in array, `z`.

```
void arrayProduct(double x, double *y, double *z, int n)
{
    int i;

    for (i=0; i<n; i++) {
        z[i] = x * y[i];
    }
}
```

### Create Source File

Open MATLAB Editor, create a file, and document the MEX file with the following information.

```
/*
 * arrayProduct.c - example in MATLAB External Interfaces
 *
 * Multiplies an input scalar (multiplier)
 * times a 1xN matrix (inMatrix)
 * and outputs a 1xN matrix (outMatrix)
 *
 * The calling syntax is:
 *
 * outMatrix = arrayProduct(multiplier, inMatrix)
 *
 * This is a MEX file for MATLAB.
 */
```

Add the C/C++ header file, `mex.h`, containing the MATLAB API function declarations.

```
#include "mex.h"
```

Save the file on your MATLAB path, for example, in `c:\work`, and name it `arrayProduct.c`. The name of your MEX file is `arrayProduct`.

## Create Gateway Routine

Every C program has a `main()` function. MATLAB uses the gateway routine, `mexFunction`, as the entry point to the function. Add the following `mexFunction` code.

```
/* The gateway function */
void mexFunction(int nlhs, mxArray *plhs[],
                 int nrhs, const mxArray *prhs[])
{
/* variable declarations here */

/* code here */
}
```

This table describes the input parameters for `mexFunction`.

Parameter	Description
<code>nlhs</code>	Number of output (left-side) arguments, or the size of the <code>plhs</code> array.
<code>plhs</code>	Array of output arguments.
<code>nrhs</code>	Number of input (right-side) arguments, or the size of the <code>prhs</code> array.
<code>prhs</code>	Array of input arguments.

## Verify MEX File Input and Output Parameters

Verify the number of MEX file input and output arguments using the `nrhs` and `nlhs` arguments.

To check for two input arguments, `multiplier` and `inMatrix`, use this code.

```
if(nrhs != 2) {
    mexErrMsgIdAndTxt("MyToolbox:arrayProduct:nrhs",
                     "Two inputs required.");
}
```

Use this code to check for one output argument, the product `outMatrix`.

```
if(nlhs != 1) {
    mexErrMsgIdAndTxt("MyToolbox:arrayProduct:nlhs",
                     "One output required.");
}
```

```
}
```

Verify the argument types using the `plhs` and `prhs` arguments. This code validates that `multiplier`, represented by `prhs[0]`, is a scalar.

```
/* make sure the first input argument is scalar */
if( !mxIsDouble(prhs[0]) ||
    mxIsComplex(prhs[0]) ||
    mxGetNumberOfElements(prhs[0]) != 1 ) {
    mexErrMsgIdAndTxt("MyToolbox:arrayProduct:notScalar",
        "Input multiplier must be a scalar.");
}
```

This code validates that `inMatrix`, represented by `prhs[1]`, is type `double`.

```
if( !mxIsDouble(prhs[1]) ||
    mxIsComplex(prhs[1])) {
    mexErrMsgIdAndTxt("MyToolbox:arrayProduct:notDouble",
        "Input matrix must be type double.");
}
```

Validate that `inMatrix` is a row vector.

```
/* check that number of rows in second input argument is 1 */
if(mxGetM(prhs[1]) != 1) {
    mexErrMsgIdAndTxt("MyToolbox:arrayProduct:notRowVector",
        "Input must be a row vector.");
}
```

### Create Computational Routine

Add the `arrayProduct` code. This function is your *computational routine*, the source code that performs the functionality you want to use in MATLAB.

```
void arrayProduct(double x, double *y, double *z, int n)
{
    int i;

    for (i=0; i<n; i++) {
        z[i] = x * y[i];
    }
}
```

A computational routine is optional. Alternatively, you can place the code within the `mexFunction` function block.

## Write Code for Cross-Platform Flexibility

MATLAB provides a preprocessor macro, `mwSize`, that represents size values for integers, based on the platform. The computational routine declares the size of the array as `int`. Replace the `int` declaration for variables `n` and `i` with `mwSize`.

```
void arrayProduct(double x, double *y, double *z, mwSize n)
{
    mwSize i;

    for (i=0; i<n; i++) {
        z[i] = x * y[i];
    }
}
```

## Declare Variables for Computational Routine

Put the following variable declarations in `mexFunction`.

- Declare variables for the input arguments.

```
double multiplier;      /* input scalar */
double *inMatrix;      /* 1xN input matrix */
```

- Declare `ncols` for the size of the input matrix.

```
mwSize ncols;          /* size of matrix */
```

- Declare the output argument, `outMatrix`.

```
double *outMatrix;     /* output matrix */
```

Later you assign the `mexFunction` arguments to these variables.

## Read Input Data

To read the scalar input, use the `mxGetScalar` function.

```
/* get the value of the scalar input */
multiplier = mxGetScalar(prhs[0]);
```

Use the `mxGetPr` function to point to the input matrix data.

```
/* create a pointer to the real data in the input matrix */
inMatrix = mxGetPr(prhs[1]);
```

Use the `mxGetN` function to get the size of the matrix.

```
/* get dimensions of the input matrix */
ncols = mxGetN(prhs[1]);
```

### Prepare Output Data

To create the output argument, `plhs[0]`, use the `mxCreateDoubleMatrix` function.

```
/* create the output matrix */
plhs[0] = mxCreateDoubleMatrix(1,ncols,mxREAL);
```

Use the `mxGetPr` function to assign the `outMatrix` argument to `plhs[0]`

```
/* get a pointer to the real data in the output matrix */
outMatrix = mxGetPr(plhs[0]);
```

### Perform Calculation

Pass the arguments to `arrayProduct`.

```
/* call the computational routine */
arrayProduct(multiplier,inMatrix,outMatrix,ncols);
```

### View Complete Source File

Compare your source file with `arrayProduct.c`, located in `matlabroot/extern/examples/mex`. Open the file in the editor.

### Build Binary MEX File

At the MATLAB command prompt, build the binary MEX file.

```
mex arrayProduct.c
```

### Test the MEX File

```
s = 5;
A = [1.5, 2, 9];
B = arrayProduct(s,A)

B =
    7.5000    10.0000    45.0000
```

### Validate MEX File Input Arguments

It is good practice to validate the type of a MATLAB variable before calling a MEX file. To test the input variable, `inputArg`, and convert it to `double`, if necessary, use this code.



```
A = [1.5, 2, 9];
inputArg = int16(A);
if ~strcmp(class(inputArg), 'double')
    inputArg = double(inputArg);
end
B = arrayProduct(s, inputArg)
```

## See Also

[mexFunction](#) | [mwSize](#) | [mxCreateDoubleMatrix](#) | [mxGetN](#) | [mxGetPr](#) | [mxGetScalar](#)

## Related Examples

- [arrayProduct.c](#)

## More About

- “Creating C++ MEX Files” on page 5-13

## Table of MEX File Source Code Files

Source code for the MEX examples shown in the following table is in subfolders of *matlabroot/extern/examples*. Make sure that you have a MATLAB-supported compiler installed.

To build a code example, first copy the file to a writable folder on your path:

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'foldername', ...
    'filename'), '.', 'f')
```

where *filename* is the name of the example, for example `arrayProduct.c`, and *foldername* is the subfolder name, for example `mex`.

You can create and compile MEX files in MATLAB or at your operating system prompt. At either prompt, type:

```
mex -v filename
```

For examples listing multiple Fortran sources files, both files are required to build the MEX file.

```
mex -v file1.F file2.F
```

You can modify the source code for the examples. For convenience, the example instructions open the files in MATLAB Editor, but you can use any code development editor.

Example Name	Example Subfolder	Description	Example
arrayFillGetPr	refbook	Fill mxArray using mxGetPr.	“Fill mxArray” on page 5-44
arrayFillSetDa	refbook	Fill mxArray with non-double values.	“Fill mxArray” on page 5-44
arrayFillSetPr	refbook	Fill mxArray using mxSetPr to allocate memory dynamically.	“Fill mxArray” on page 5-44
arrayProduct.c	mex	Multiply a scalar times 1xN matrix.	“Create C Source MEX File” on page 5-18

Example Name	Example Subfolder	Description	Example
arraySize.c	mex	Illustrate memory requirements of large mxArray.	“Handling Large mxArrays” on page 5-62
convec.c convec.F	refbook	Pass complex data.	“Handle Complex Data” on page 5-47
dblmat.F compute.F	refbook	Use of Fortran %VAL.	
dotProductCon	refbook	Handle Fortran complex return type for function called from a C MEX file.	“Handling Complex Numbers in LAPACK and BLAS Functions” on page 4-31
doubleelement	refbook	Use unsigned 16-bit integers.	“Handle 8-, 16-, and 32-Bit Data” on page 5-48
explore.c	mex	Identify data type of input variable.	“Work with mxArrays” on page 2-17
findnz.c	refbook	Use N-dimensional arrays.	“Manipulate Multidimensional Numerical Arrays” on page 5-49
fulltosparse.c fulltosparse.F, loadsparse.F	refbook	Populate a sparse matrix.	“Handle Sparse Arrays” on page 5-51
matrixDivide.c	refbook	Call a LAPACK function.	“Preserving Input Values from Modification” on page 4-28
matrixDivideC	refbook	Call a LAPACK function with complex numbers.	“Handling Complex Numbers in LAPACK and BLAS Functions” on page 4-31
matrixMultiply	refbook	Call a BLAS function.	“Passing Arguments to Fortran Functions from C/C++ Programs” on page 4-29
matsq.F	refbook	Pass matrices in Fortran.	
matsqint8.F	refbook	Pass non-double matrices in Fortran.	

Example Name	Example Subfolder	Description	Example
mexatexit.c mexatexit.cpp	mex	Register an exit function to close a data file.	“Handle Files with C++” on page 5-16
mexcallmatlab	mex	Call built-in MATLAB disp function.	
mexcallmatlab	mex	How to capture error information.	
mexcpp.cpp	mex	Illustrate some C++ language features in a MEX file.	“C++ Class in MEX Files” on page 5-15
mexevalstring	mex	Use <code>mexEvalString</code> to assign variables in MATLAB.	<code>mexEvalString</code>
mexfunction.c	mex	How to use <code>mexFunction</code> .	<code>mexFunction</code>
mexgetproperty	mex	Use <code>mxGetProperty</code> and <code>mxSetProperty</code> to change the <code>Color</code> property of a graphic object.	<code>mxGetProperty</code> and <code>mxSetProperty</code>
mexgetarray.c	mex	Use <code>mexGetVariable</code> and <code>mexPutVariable</code> to track counters in the MEX file and in the MATLAB global workspace.	<code>mexGetVariable</code> and <code>mexPutVariable</code>
mexlock.c mexlockf.F	mex	How to lock and unlock a MEX file.	<code>mexLock</code>
mxcalcsinglesu	mx	Demonstrate MATLAB 1-based matrix indexing versus C 0-based indexing.	<code>mxCalcSingleSubscript</code>
mxcreatecellm mxcreatecellm	mx	Create 2-D cell array.	“Create 2-D Cell Array” on page 5-43
mxcreatechar	mx	Create 2-D character array.	<code>mxCreateCharMatrixFromStrings</code>
mxcreatestruct	mx	Create MATLAB structure from C structure.	<code>mxCreateStructArray</code>

Example Name	Example Subfolder	Description	Example
mxcreateunini	mx	Create an uninitialized mxArray, fill with local data, and return.	mxCreateUninitNumericMatrix
mxgeteps.c mxgetepsf.F	mx	Read MATLAB eps value.	mxGetEps
mxgetinf.c	mx	Read inf value.	mxGetInf
mxgetnzmax.c	mx	Display number of nonzero elements in a sparse matrix and maximum number of nonzero elements it can store.	mxGetNzmax
mxisclass.c	mx	Check if array is member of specified class.	mxIsClass
mxisfinite.c	mx	Check for NaN and infinite values.	mxIsFinite
mxislogical.c	mx	Check if workspace variable is logical or global.	mxIsLogical
mxisscalar.c	mx	Check if input variable is scalar.	mxIsScalar
mxmalloc.c	mx	Allocate memory to copy a MATLAB char array to a C-style string.	mxMalloc
mxsetdimensionc mxsetdimensionc	mx	Reshape an array.	mxSetDimensions
mxsetnzmax.c	mx	Reallocate memory for sparse matrix and reset values of pr, pi, ir, and nzmax.	mxSetNzmax
passstr.F	refbook	Pass C character matrix from Fortran to MATLAB.	
phonebook.c	refbook	Manipulate structures and cell arrays.	“Pass Structures and Cell Arrays” on page 5-42

Example Name	Example Subfolder	Description	Example
revord.c revord.F	refbook	Copy MATLAB char array to and from C-style string.	“Pass Strings” on page 5-35
sincall.c sincall.F, fill.F	refbook	Create mxArray and pass to MATLAB sin and plot functions	
timestwo.c timestwo.F	refbook	Demonstrate common workflow of MEX file.	“Pass Scalar Values” on page 5-32
utdu_slv.c	refbook	Use LAPACK for symmetric indefinite factorization.	“Handling Complex Numbers in LAPACK and BLAS Functions” on page 4-31
xtimesy.c xtimesy.F	refbook	Pass multiple parameters.	
yprime.c yprimef.F, yprimefg.F	mex	Solve simple three body orbit problem.	

## Choose a C++ Compiler

### Select Microsoft Visual Studio Compiler

This example shows how to determine and change the default compiler for building C++ MEX files when you have multiple versions of Microsoft Visual Studio on your system. The messages in this example assume that you have Microsoft Visual C++ 2012 and Microsoft Visual C++ 2015. Use these steps for any C++ compilers on your system.

MATLAB chooses a default compiler for C source files and a default compiler for C++ source files. To see the default C++ compiler, type:

```
mex -setup c++
```

```
MEX configured to use 'Microsoft Visual C++ 2012' for C++ language compilation.
```

MATLAB also displays links to other C++ compilers installed on your system.

To change the default to MSVC 2015, click the link:

```
Microsoft Visual C++ 2015 Professional \(C\)
```

```
MEX configured to use 'Microsoft Visual C++ 2015 Professional (C)' for C++ language compilation.
```

Microsoft Visual C++ 2015 remains the default until you call `mex -setup c++` to select a different default.

When you call the `mex` command with a source file, MATLAB displays the name of the compiler used to build the MEX file. You can also find this information using the `mex -setup lang` command. By default, when you type `mex -setup`, MATLAB shows you information for the C compiler only. If you want information for C++ compilers, type:

```
mex -setup c++
```

### Select MinGW-w64 Compiler

If you only have the MinGW compiler installed on your system, the `mex` command automatically chooses MinGW for both C and C++ MEX files. If you have multiple C or C++ compilers, use `mex -setup` to choose MinGW for both C and C++ MEX files.

```
mex -setup  
mex -setup cpp
```

If you only type `mex -setup` choosing MinGW, when you compile a C++ file, `mex` might choose a different compiler.

### **More About**

- “Change Default Compiler” on page 4-20



## Set Up C/C++ Examples

The Matrix Library provides a full set of routines that handle the types supported by MATLAB. For each data type, there is a specific set of functions that you can use for data manipulation. The first example discusses the simple case of doubling a scalar. After that, the examples discuss how to pass in, manipulate, and pass back various data types, and how to handle multiple inputs and outputs. Finally, the sections discuss passing and manipulating various MATLAB types.

Source code for the examples in this section is in the `matlabroot/extern/examples/refbook` folder. To build an example, first copy the file to a writable folder on your path:

```
copyfile(fullfile(matlabroot,'extern','examples','refbook',...  
    'filename.c'),'.','f')
```

where *filename* is the name of the example.

At the MATLAB command prompt, type:

```
mex filename.c
```

The following topics look at source code for the examples. Unless otherwise specified, the term "MEX file" refers to a source file.

For a list of MEX example files available with MATLAB, see "Table of MEX File Source Code Files" on page 5-24.

## Pass Scalar Values

<b>In this section...</b>
“Pass Scalar as Matrix” on page 5-32
“Pass Scalar by Value” on page 5-33

### Pass Scalar as Matrix

This example shows how to write a MEX file that passes scalar values.

Suppose that you have the following C code, `timestwo`, that takes a scalar input, a 1-by-1 matrix, and doubles it.

```
void timestwo(double y[], double x[])
{
    y[0] = 2.0*x[0];
    return;
}
```

### C Code Analysis

To see the function written as a MEX file, open the file, `timestwo.c`, in the MATLAB Editor.

In C/C++, the compiler checks function arguments for number and type. However, in MATLAB, you can pass any number or type of arguments to a function; the function is responsible for argument checking. MEX files also allow variable inputs. Your MEX file must safely handle any number of input or output arguments of any supported type.

This code checks for the proper number of arguments.

```
if(nrhs != 1) {
    mexErrMsgIdAndTxt( "MATLAB:timestwo:invalidNumInputs",
        "One input required.");
} else if(nlhs>1) {
    mexErrMsgIdAndTxt( "MATLAB:timestwo:maxlhs",
        "Too many output arguments.");
}
```

This code checks if the input is a scalar double value.

```

mrows = mxGetM(prhs[0]);
ncols = mxGetN(prhs[0]);
if( !mxIsDouble(prhs[0]) || mxIsComplex(prhs[0]) ||
    !(mrows==1 && ncols==1) ) {
    mexErrMsgIdAndTxt( "MATLAB:timestwo:inputNotRealScalarDouble",
        "Input must be a noncomplex scalar double.");
}

```

### Build and Test Example

Build the MEX file.

```
mex -v timestwo.c
```

Call the function.

```

x = 2;
y = timestwo(x)

y =
     4

```

### Pass Scalar by Value

This example shows how to write a MEX file that passes a scalar by value.

The `mxGetScalar` function returns the value of a scalar instead of a pointer to a copy of the scalar variable, `x`.

The following C code implements the `timestwo_alt` function.

```

void timestwo_alt(double *y, double x)
{
    *y = 2.0*x;
}

```

Compare the `timestwo_alt` function signature with the `timestwo` function signature.

```

void timestwo_alt(double *y, double x)
void timestwo(double y[], double x[])

```

The input value `x` is a scalar of type `double`. In the `timestwo` function, the input value is a matrix of type `double`.

To see the function written as a MEX file, open the file, `timestwoalt.c`, in the MATLAB Editor.

Compare the call to `timestwo_alt` to the call to `timestwo`.

```
/* Get the scalar value of the input x */
/* note: mxGetScalar returns a value, not a pointer */
x = mxGetScalar(prhs[0]);

/* Assign a pointer to the output */
y = mxGetPr(plhs[0]);

/* Call the timestwo_alt subroutine */
timestwo_alt(y,x);

/* Assign pointers to each input and output. */
x = mxGetPr(prhs[0]);
y = mxGetPr(plhs[0]);

/* Call the timestwo subroutine. */
timestwo(y,x);
```

The value `x`, created by `mxGetScalar`, is a scalar not a pointer.

## Pass Strings

This example shows how to pass strings to a MEX file. The example `revord.c` accepts a character vector and returns the characters in reverse order.

### C Code Analysis

To see the code, open the file, `revord.c`, in the MATLAB Editor.

The gateway function, `mexFunction`, creates a C string from the input variable, `prhs[0]`. By isolating variables of type `mxArray` from the computational subroutine, `revord`, you can avoid making significant changes to your original C and C++ code.

Convert the input argument, `prhs[0]`, to a C-style string, `input_buf`.

```
input_buf = mxArrayToString(prhs[0]);
```

Allocate memory for the output argument, `output_buf`, a C-style string.

```
output_buf = mxMalloc(buflen, sizeof(char));
```

The size of the output argument is equivalent to the size of the input argument.

Call the computational subroutine, `revord`.

```
revord(input_buf, buflen, output_buf);
```

Convert the output, `output_buf`, to an `mxArray` and assign to `plhs[0]`.

```
plhs[0] = mxCreateString(output_buf);
```

Do not release memory for this variable because it is an output argument.

The `mxArrayToString` function, used to create the temporary `input_buf` variable, allocates memory; use the `mxFree` function to release the memory.

```
mxFree(input_buf);
```

### Build and Test Example

Run the following commands from the MATLAB command line.

Build the example.

```
mex -v revord.c
```

Call the function.

```
x = 'hello world';  
y = revord(x)
```

```
y =  
dlrow olleh
```

### Related Examples

- `revord.c`

## Handling Strings in C/C++

### In this section...

- “How MATLAB Represents Strings in MEX Files” on page 5-37
- “Character Encoding and Multibyte Encoding Schemes” on page 5-37
- “Converting MATLAB Character Vector to C-Style String” on page 5-38
- “Converting C-Style String to MATLAB Character Vector” on page 5-38
- “Returning Modified Input String” on page 5-38
- “Memory Management” on page 5-38

### How MATLAB Represents Strings in MEX Files

In C/C++ MEX files, a MATLAB character vector is an `mxArray` of type `mxChar`, using a locale-neutral data representation (Unicode encoding). MATLAB represents C-style strings as type `char`, and uses the character encoding scheme specified by the user locale setting.

The following C/C++ Matrix Library functions provides string handling functions to help you work with both `mxArrays` and C-style strings.

- `mxCreateString` — Creates a `mxChar` `mxArray` initialized to the input string.
- `mxArrayToString` — Copies a `mxChar` `mxArray` into a C-style string. Supports multibyte encoded characters.
- `mxGetString` — Copies a `mxChar` `mxArray` into a C-style string. Best used with single-byte encoded characters. Supports multibyte encoded characters when you calculate string buffer size.
- `mxGetChars` — Returns a pointer to the first `mxChar` element in the `mxArray`.

Consider the following topics when choosing a string handling function.

### Character Encoding and Multibyte Encoding Schemes

MATLAB supports the character encoding scheme specified by the user locale setting. When an MX Library function converts `mxChar` data to a C `char` type, MATLAB also converts the character to the user default encoding.

If you use a multibyte encoding scheme, use the `mxArrayToString` function.

The `mxGetChars` function provides a pointer to the `mxChar` array; it does not change the character encoding.

You can also use the `mxGetString` function with multibyte encoding schemes. `mxGetString` converts the `mxChar` data to your user default encoding, and copies the converted characters to the destination buffer. However, you must calculate the size of the destination buffer. For single-byte encoding, the size of the buffer is the number of characters, plus 1 for the null terminator. For multibyte encoding, the size of a character is one or more bytes. Some options for calculating the buffer size are to overestimate the amount (calculating the number of characters times the maximum number of bytes used by the encoding scheme), analyze the string to determine the precise size used by each character, or utilize 3rd-party string buffer libraries. After this calculation, add 1 for the null terminator.

## Converting MATLAB Character Vector to C-Style String

When you pass a character array to a MEX function, it is an `mxArray` of type `mxChar`. If you call a C function to manipulate the string, first convert the data to a C type `char` using the `mxArrayToString` or `mxGetString` functions.

## Converting C-Style String to MATLAB Character Vector

If your MEX file creates a C string and returns the data to MATLAB, use the `mxCreateString` function to copy the C string into an `mxChar` array.

## Returning Modified Input String

Suppose your MEX file takes character input, modifies it, and returns the result. Since MEX file input parameters (the `prhs` array) are read-only, you must define a separate output parameter to handle the modified string.

## Memory Management

MathWorks recommends that MEX file functions destroy their own temporary arrays and free their own dynamically allocated memory. The function you use to release memory depends on how you use the string buffer and what function you use to create the buffer.



If you call this function:	Release memory using this function:
Any string function listed here	Do not destroy an mxArray in a source MEX file when it is: <ul style="list-style-type: none"> <li>• Passed to the MEX file in the right-hand side list <code>prhs [ ]</code>.</li> <li>• Returned in the left side list <code>plhs [ ]</code>.</li> <li>• Returned by the <code>mexGetVariablePtr</code> function.</li> <li>• Used to create a structure.</li> </ul>
<code>mxArrayToString</code>	<code>mxFree</code>
<code>mxGetString</code>	When using <code>mxMalloc</code> / <code>mxMalloc</code> / <code>mxRealloc</code> to create input argument <code>buf</code> , call <code>mxFree(buf)</code> .
<code>mxCreateString</code>	<code>mxDestroyArray</code>
<code>mxGetChars</code>	None. Function creates a pointer to an mxArray but does not allocate additional memory.

## More About

- “C/C++ Matrix Library API”
- “Locale Settings for MATLAB Process”

## Pass Multiple Inputs or Outputs

This example shows how to call a MEX file with multiple inputs. The function, `xtimesy`, multiplies an input scalar by a scalar or matrix and outputs a matrix.

The `plhs[]` and `prhs[]` parameters are vectors that contain pointers to each left-side (output) variable and each right-side (input) variable, respectively. `plhs[0]` contains a pointer to the first left-side argument, `plhs[1]` contains a pointer to the second left-side argument, and so on. Likewise, `prhs[0]` contains a pointer to the first right-side argument, `prhs[1]` points to the second, and so on.

### C Code Analysis

To see the code, open the file, `xtimesy.c`, in the MATLAB Editor.

Get the scalar input value, `x`.

```
x = mxGetScalar(prhs[0]);
```

Get the second input, `y`, which can be either a scalar or a matrix.

```
y = mxGetPr(prhs[1]);
```

Create the output argument, `plhs[0]`, which is the same size as argument `y`.

```
/* get the dimensions of the matrix input y */
mrows = mxGetM(prhs[1]);
ncols = mxGetN(prhs[1]);

/* set the output pointer to the output matrix */
plhs[0] = mxCreateDoubleMatrix( (mwSize)mrows, (mwSize)ncols, mxREAL);
```

### Build and Test Example

Run the following commands from the MATLAB command line.

Build the example.

```
mex -v xtimesy.c
```

Call the function with scalar values.

```
x = 7;
y = 7;
```

```
z = xtimesy(x,y)
```

```
z =  
    49
```

Call the function with a matrix.

```
x = 9;  
y = ones(3);  
z = xtimesy(x,y)
```

```
z =  
     9     9     9  
     9     9     9  
     9     9     9
```

## Related Examples

- `xtimesy.c`

## Pass Structures and Cell Arrays

Passing structures and cell arrays into MEX files is like passing any other data type, except the data itself is of type `mxArray`. In practice, `mxGetField` (for structures) and `mxGetCell` (for cell arrays) return pointers of type `mxArray`. You treat the pointers like any other pointers of type `mxArray`. To pass the data contained in the `mxArray` to a C/C++ routine, use an API function such as `mxGetData` to access it.

This example takes an `m-by-n` structure matrix as input and returns a new `1-by-1` structure that contains these fields:

- Text input generates an `m-by-n` cell array
- Numeric input (noncomplex, scalar values) generates an `m-by-n` vector of numbers with the same class ID as the input, for example `int`, `double`, and so on.

To build this example, at the command prompt type:

```
mex phonebook.c
```

To see how this program works, enter this structure:

```
friends(1).name = 'Jordan Robert';  
friends(1).phone = 3386;  
friends(2).name = 'Mary Smith';  
friends(2).phone = 3912;  
friends(3).name = 'Stacy Flora';  
friends(3).phone = 3238;  
friends(4).name = 'Harry Alpert';  
friends(4).phone = 3077;
```

Call the MEX file:

```
phonebook(friends)  
  
ans =  
    name: {1x4 cell }  
    phone: [3386 3912 3238 3077]
```

### Related Examples

- `phonebook.c`

## Create 2-D Cell Array

This example shows how to create a cell array in a MEX file, using the `mxcreatecellmatrix.c` function, which places input arguments in a cell array.

### C Code Analysis

To see the code, open the file in MATLAB Editor.

Create a cell array for the number of input arguments.

```
cell_array_ptr = mxCreateCellMatrix((mwSize)nrhs,1);
```

Copy the input arguments into the cell array.

```
for( i=0; i<(mwIndex)nrhs; i++){  
    mxSetCell(cell_array_ptr,i,mxDuplicateArray(prhs[i]));
```

### Build and Test Example

Run the following commands from the MATLAB command line.

Build the example.

```
mex -v mxcreatecellmatrix.c
```

Create input arguments.

```
str1 = 'hello';  
str2 = 'world';  
num = 2012;
```

Create a 3-x-1 cell array and call `disp` to display the contents.

```
mxcreatecellmatrix(str1,str2,num)
```

The contents of the created cell is:

```
'hello'  
'world'  
[2012]
```

### Related Examples

- `mxcreatecellmatrix.c`

## Fill mxArray

### In this section...

“Options” on page 5-44

“Copying Data Directly into an mxArray” on page 5-44

“Pointing to Data” on page 5-44

### Options

You can move data from a C/C++ program into an mxArray using the Matrix Library. The functions you use depend on the type of data in your application. Use the `mxSetPr` and `mxGetPr` functions for data of type `double`. For numeric data other than `double`, use the `mxSetData` function. For nonnumeric data, see the examples for the `mxCreateString` function.

The following examples use a variable, `data`, to represent data from a computational routine. Each example creates an mxArray using the `mxCreateNumericMatrix` function, fills it with `data`, and returns it as the output argument `plhs[0]`.

These examples use real data only. If you have complex data, use the `mxGetPi` and `mxSetPi` functions as needed.

### Copying Data Directly into an mxArray

The `arrayFillGetPr.c` example uses the `mxGetPr` function to copy the values from `data` to `plhs[0]`.

### Pointing to Data

The `arrayFillSetPr.c` example uses the `mxSetPr` function to point `plhs[0]` to `data`.

The example `arrayFillSetData.c` shows how to fill an mxArray for numeric types other than `double`.

### See Also

`mxCreateString` | `mxGetPr` | `mxSetData` | `mxSetPr`

## Related Examples

- `arrayFillGetPr.c`
- `arrayFillSetPr.c`
- `arrayFillSetData.c`

## Prompt User for Input

Because MATLAB does not use `stdin` and `stdout`, do not use C/C++ functions like `scanf` and `printf` to prompt for user input. The following example shows how to use `mexCallMATLAB` with the `input` function to get a number from the user.

```
#include "mex.h"
#include "string.h"
void mexFunction( int nlhs, mxArray *plhs[],
                  int nrhs, const mxArray *prhs[] )
{
    mxArray  *new_number, *str;
    double out;

    str = mxCreateString("Enter extension: ");
    mexCallMATLAB(1,&new_number,1,&str,"input");
    out = mxGetScalar(new_number);
    mexPrintf("You entered: %.0f ", out);
    mxDestroyArray(new_number);
    mxDestroyArray(str);
    return;
}
```

### See Also

[input](#) | [inputdlg](#) | [mexCallMATLAB](#)



## Handle Complex Data

MATLAB separates complex data into real and imaginary parts. The MATLAB API provides two functions, `mxGetPr` and `mxGetPi`, that return pointers (of type `double *`) to the real and imaginary parts of your data.

This example, `convec.c`, takes two complex row vectors and convolves them.

To build this example, at the command prompt type:

```
mex convec.c
```

Enter these numbers at the MATLAB prompt.

```
x = [3.000 - 1.000i, 4.000 + 2.000i, 7.000 - 3.000i];  
y = [8.000 - 6.000i, 12.000 + 16.000i, 40.000 - 42.000i];
```

Call the MEX file.

```
z = convec(x,y)
```

```
z =  
    1.0e+02 *
```

```
Columns 1 through 4
```

```
0.1800 - 0.2600i 0.9600 + 0.2800i 1.3200 - 1.4400i 3.7600 - 0.1200i
```

```
Column 5
```

```
1.5400 - 4.1400i
```

Compare the results with the built-in MATLAB function `conv`.

### See Also

`mxGetPi` | `mxGetPr`

### Related Examples

- `convec.c`

## Handle 8-, 16-, and 32-Bit Data

The MATLAB API provides a set of functions that support signed and unsigned 8-, 16-, and 32-bit data. For example, the `mxCreateNumericArray` function constructs an unpopulated N-dimensional numeric array with a specified data size. For more information, see `mxClassID`.

Once you have created an unpopulated MATLAB array of a specified data type, you can access the data using `mxGetData` and `mxGetImagData`. These two functions return pointers to the real and imaginary data. You can perform arithmetic on data of 8-, 16-, or 32-bit precision in MEX files and return the result to MATLAB, which recognizes the correct data class.

The example, `doubleelement.c`, constructs a 2-by-2 matrix with unsigned 16-bit integers, doubles each element, and returns both matrices to MATLAB.

To build this example, at the command prompt type:

```
mex doubleelement.c
```

Call the example.

```
doubleelement
```

```
ans =  
     2     6  
     4     8
```

The output of this function is a 2-by-2 matrix populated with unsigned 16-bit integers.

### See Also

`mxClassID` | `mxCreateNumericArray` | `mxGetData` | `mxGetImagData`

### Related Examples

- `doubleelement.c`

## Manipulate Multidimensional Numerical Arrays

You can manipulate multidimensional numerical arrays by using `mxGetData` and `mxGetImagData`. These functions return pointers to the real and imaginary parts of the data stored in the original multidimensional array. The example, `findnz.c`, takes an N-dimensional array of doubles and returns the indices for the nonzero elements in the array.

Build the example.

```
mex findnz.c
```

Create a sample matrix.

```
matrix = [ 3 0 9 0; 0 8 2 4; 0 9 2 4; 3 0 9 3; 9 9 2 0]
```

```
matrix =  
  3   0   9   0  
  0   8   2   4  
  0   9   2   4  
  3   0   9   3  
  9   9   2   0
```

`findnz` determines the position of all nonzero elements in the matrix.

```
nz = findnz(matrix)
```

```
nz =  
  1   1  
  4   1  
  5   1  
  2   2  
  3   2  
  5   2  
  1   3  
  2   3  
  3   3  
  4   3  
  5   3  
  2   4  
  3   4  
  4   4
```

## **See Also**

`mxGetData` | `mxGetImagData`

## **Related Examples**

- `findnz.c`

## Handle Sparse Arrays

The MATLAB API provides a set of functions that allow you to create and manipulate sparse arrays from within your MEX files. These API routines access and manipulate `ir` and `jc`, two of the parameters associated with sparse arrays. For more information on how MATLAB stores sparse arrays, see “The MATLAB Array” on page 4-7.

The example `fulltosparse.c` shows how to populate a sparse matrix.

Build the example.

```
mex fulltosparse.c
```

Create a full, 5-by-5 identity matrix.

```
full = eye(5)
```

```
full =  
    1    0    0    0    0  
    0    1    0    0    0  
    0    0    1    0    0  
    0    0    0    1    0  
    0    0    0    0    1
```

Call `fulltosparse` to produce the corresponding sparse matrix.

```
spar = fulltosparse(full)
```

```
spar =  
    (1,1)    1  
    (2,2)    1  
    (3,3)    1  
    (4,4)    1  
    (5,5)    1
```

### Related Examples

- `fulltosparse.c`

## Call MATLAB Functions from C/C++ MEX Files

It is possible to call MATLAB functions, operators, user-defined functions, and other binary MEX files from within your C/C++ source code by using the API function `mexCallMATLAB`.

The example, `sincall.c`, creates an `mxArray`, passes various pointers to a local function to acquire data, and calls `mexCallMATLAB` to calculate the `sine` function and plot the results.

To build this example, at the command prompt type:

```
mex sincall.c
```

Run the example.

```
sincall
```

MATLAB displays a sin curve equivalent to executing the following MATLAB commands:

```
MAX = 1000;
```

```
mm = MAX/2;
```

```
for i = 1:mm-1
```

```
    X(i) = i*(4*3.14159/MAX);
```

```
end
```

```
Y = sin(X);
```

```
plot(X,Y)
```

### See Also

`mexCallMATLAB`

### Related Examples

- `sincall.c`

## Debug on Microsoft Windows Platforms

This example shows how to debug `yprime.c`, found in your `matlabroot/extern/examples/mex/` folder, with Microsoft Visual Studio 2012.

- 1 Make sure Visual Studio is your selected C compiler:

```
cc = mex.getCompilerConfigurations('C','Selected');
cc.Name
```

```
ans =
```

```
Microsoft Visual C++ 2012 (C)
```

- 2 Compile the source MEX file with the `-g` option, which builds the file with debugging symbols included. For example:

```
copyfile(fullfile(matlabroot,'extern','examples','mex','yprime.c'),'.','f')
mex -g yprime.c
```

- 3 Start Visual Studio. Do not exit your MATLAB session.
- 4 From the Visual Studio **Tools** menu, select **Attach to Process**
- 5 In the Attach to Process dialog box, select the MATLAB process and click **Attach**.

Visual Studio loads data then displays an empty code pane.

- 6 Open the source file `yprime.c` by selecting **File > Open > File**. Locate `yprime.c` in the folder, `c:\work`.
- 7 Set a breakpoint by right-clicking the desired line of code and following **Breakpoint > Insert Breakpoint** on the context menu. It is often convenient to set a breakpoint at `mexFunction` to stop at the beginning of the gateway routine.

If you have not yet run the executable file, ignore any “!” icon that appears with the breakpoint next to the line of code.

Once you hit one of your breakpoints, you can make full use of any commands the debugger provides to examine variables, display memory, or inspect registers.

- 8 Open MATLAB and type:

```
yprime(1,1:4)
```

`yprime.c` is opened in the Visual Studio debugger at the first breakpoint.

- 9 If you select **Debug > Continue**, MATLAB displays:

```
ans =  
    2.0000    8.9685    4.0000   -1.0947
```

For more information on how to debug in the Visual Studio environment, see your Microsoft documentation.

### Notes on Debugging

Binary MEX files built with the `-g` option do not execute on other computers because they rely on files that are not distributed with MATLAB. For more information on isolating problems with MEX files, see “Troubleshoot MEX Files”.

### More About

- “Debug in Simulink Environment”
- “MATLAB Code Analysis”



## Debug on Linux Platforms

The GNU<sup>®</sup> Debugger `gdb`, available on Linux systems, provides complete source code debugging, including the ability to set breakpoints, examine variables, and step through the source code line-by-line.

In this procedure, the MATLAB command prompt `>>` is shown in front of MATLAB commands, and `linux>` represents a Linux prompt; your system might show a different prompt. The debugger prompt is `<gdb>`.

To debug with `gdb`:

- 1 Compile the source MEX file with the `-g` option, which builds the file with debugging symbols included. For this example, at the Linux prompt, type:

```
linux> mex -g yprime.c
```

- 2 At the Linux prompt, start the `gdb` debugger using the `matlab -D` option.

```
linux> matlab -Dgdb
```

- 3 Tell `gdb` to stop for debugging.

```
<gdb> handle SIGSEGV SIGBUS nostop noprint
```

- 4 Start MATLAB without the Java<sup>®</sup> Virtual Machine (JVM<sup>™</sup>) by using the `-nojvm` startup flag.

```
<gdb> run -nojvm
```

- 5 In MATLAB, enable debugging with the `dbmex` function and run your binary MEX file.

```
>> dbmex on  
>> yprime(1,1:4)
```

- 6 You are ready to start debugging.

It is often convenient to set a breakpoint at `mexFunction` so you stop at the beginning of the gateway routine.

```
<gdb> break mexFunction  
<gdb> r
```

- 7 Once you hit one of your breakpoints, you can make full use of any commands the debugger provides to examine variables, display memory, or inspect registers.

To proceed from a breakpoint, type:

```
<gdb> continue
```

- 8** After stopping at the last breakpoint, type:

```
<gdb> continue
```

`yprime` finishes and MATLAB displays:

```
ans =
```

```
2.0000 8.9685 4.0000 -1.0947
```

- 9** From the MATLAB prompt you can return control to the debugger by typing:

```
>> dbmex stop
```

Or, if you are finished running MATLAB, type:

```
>> quit
```

- 10** When you are finished with the debugger, type:

```
<gdb> quit
```

You return to the Linux prompt.

Refer to the documentation provided with your debugger for more information on its use.

## See Also

`dbmex`

# Debug on Mac Platforms

## In this section...

“Using Xcode” on page 5-57

“Using LLDB” on page 5-59

## Using Xcode

This example shows how to debug the MEX file, `yprime.c`, using Xcode.

### Copy the Source MEX File

The `yprime.c` source code is in the `matlabroot` folder. In MATLAB, copy the file to a local, writable folder, for example `/usr/work/my_data`. Create the folder if it does not exist.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'mex', 'yprime.c'), ...  
fullfile('/', 'usr', 'work', 'my_data'))
```

Set your current folder in MATLAB to `/usr/work/my_data`.

### Compile the Source MEX File

Compile the source MEX file with the `-g` option, which adds debugging symbols.

```
mex -g yprime.c
```

MATLAB creates the binary MEX file, `yprime.mexmaci64`.

### Create an Empty Xcode Project for Debugging

In Xcode,

- Select **File > New > Project**.
- In the Choose a template for your project dialog box, in the **OS X** section, select **Other**.
- Select **Empty**.
- Set **Product Name** to `debug_yprime`.

### Add yprime Files to the Project

To add breakpoints to your source code file, add the `yprime.c` file to the project. You can either drag the file directly into the project or right-click in the project and click **Add files to "debug\_yprime"** to add files.

Make sure the **Destination** option, **Copy items into destination group's folder (if needed)**, is cleared. Clearing this option enables breakpoints to be added to the file that MATLAB runs.

Click **Finish** to add the file.

### Create a Scheme

- Select **Product > Scheme > New Scheme...**
- Set **Name** to `debug`.
- Set **Target** to `None`.
- Press **OK**. The scheme editing dialog box opens.
- Set the **Run > Info > Executable** option to **Other...** In the file selection window, press the **Command+Shift+G** keyboard shortcut to toggle the **Go to the folder:** menu. Specify the full path to the MATLAB `MATLAB_maci64` executable, which you will use to debug the MEX file. An example of a full path is `/Applications/MATLAB_R2016a.app/Contents/MacOS/MATLAB_maci64`.
- Select **Wait for executable to be launched**.

### Add a Symbolic Breakpoint

Open the **Debug** menu:

- Select **Debug > Breakpoints > Create Symbolic Breakpoint**.

Set **Symbol** to `NSApplicationMain`.

Click **Add action** to add the following debugger command:

```
process handle -p true -n false -s false SIGSEGV SIGBUS
```

Check **Automatically continue after evaluating**.

### Set Breakpoints

To add a breakpoint to `yprime.c`, click the gutter next to the line where you want execution to pause. For more information, refer to the Xcode documentation.

## Start MATLAB

Click **Run** at the top left of the project window (or type **Command-R**) to start the debugger. Xcode displays a message **Waiting for MATLAB to launch**. This action might take some seconds, especially the first time you use this procedure.

Start the MATLAB executable from the Mac Terminal prompt or the Finder. For Mac startup information, see “From Terminal Window”.

## Run the Binary MEX File in MATLAB

In MATLAB, change the current folder to the folder with the `yprime` files.

Run the binary MEX file.

```
yprime(1,1:4)
```

The debugger opens `yprime.c` at the first breakpoint.

Press **Continue**. MATLAB displays:

```
ans =  
    2.0000    8.9685    4.0000   -1.0947
```

## Using LLDB

LLDB is the debugger available with Xcode on Mac OS X systems. Refer to the documentation provided with your debugger for more information on its use.

In this procedure, `>>` indicates the MATLAB command prompt, and `%` represents a Mac Terminal prompt. The debugger prompt is `(lldb)`.

- “Debug MEX Without JVM” on page 5-59
- “Debug MEX with JVM” on page 5-61

## Debug MEX Without JVM

This example debugs the `yprime` MEX file without the Java Virtual Machine (JVM). Running MATLAB in this mode minimizes memory usage and improves initial startup speed, but restricts functionality. For example, you cannot use the desktop.

- 1 Compile the source MEX file with the `-g` option, which builds the file with debugging symbols included. At the Terminal prompt, type:

```
% mex -g yprime.c
```

- 2 Start the lldb debugger using the `matlab` function `-D` option:

```
% matlab -Dlldb
```

- 3 Start MATLAB using the `-nojvm` startup flag:

```
(lldb) run -nojvm
```

- 4 In MATLAB, enable debugging with the `dbmex` function and run your MEX file:

```
>> dbmex on  
>> yprime(1,1:4)
```

The debugger traps a user-defined signal and the prompt returns to lldb.

- 5 You are ready to start debugging.

It is often convenient to set a breakpoint at `mexFunction` so you stop at the beginning of the gateway routine.

```
(lldb) b mexFunction
```

- 6 Once you hit a breakpoint, you can use any debugger commands to examine variables, display memory, or inspect registers. To proceed from a breakpoint, type:

```
(lldb) c
```

- 7 After stopping at the last breakpoint, type:

```
(lldb) c
```

`yprime` finishes and MATLAB displays:

```
ans =  
    2.0000    8.9685    4.0000   -1.0947
```

- 8 From the MATLAB prompt, return control to the debugger by typing:

```
>> dbmex stop
```

Or, if you are finished running MATLAB, type:

```
>> quit
```

- 9 When you are finished with the debugger, type:

```
(lldb) q
```

You return to the Terminal prompt.

### **Debug MEX with JVM**

To debug a MEX file with the JVM, first handle `SIGSEGV` and `SIGBUS` process signals. Start MATLAB and stop at the first instruction.

- At the Terminal prompt, compile the MEX file and start the lldb debugger.

```
% mex -g yprime.c  
% matlab -Dlldb
```

- Start MATLAB.

```
(lldb) process launch -s
```

- Tell the process to continue when these process signals occur.

```
(lldb) process handle -p true -n false -s false SIGSEGV SIGBUS
```

- You can set break points and execute other debugger commands.

### **More About**

- “Start MATLAB on Mac Platforms”

## Handling Large mxArray

### In this section...

“Using the 64-Bit API” on page 5-62

“Building the Binary MEX File” on page 5-64

“Example” on page 5-64

“Caution Using Negative Values” on page 5-64

“Building Cross-Platform Applications” on page 5-65

Binary MEX files built on 64-bit platforms can handle 64-bit mxArray. These large data arrays can have up to  $2^{48}-1$  elements. The maximum number of elements a sparse mxArray can have is  $2^{48}-2$ .

Using the following instructions creates platform-independent binary MEX files as well.

Your system configuration can affect the performance of MATLAB. The 64-bit processor requirement enables you to create the mxArray and access data in it. However, the system memory, in particular the size of RAM and virtual memory, determine the speed at which MATLAB processes the mxArray. The more memory available, the faster the processing.

The amount of RAM also limits the amount of data you can process at one time in MATLAB. For guidance on memory issues, see “Strategies for Efficient Use of Memory”. Memory management within source MEX files can have special considerations, as described in “Memory Management” on page 5-66.

### Using the 64-Bit API

The signatures of the API functions shown in the following table use the mwSize or mwIndex types to work with a 64-bit mxArray. The variables you use in your source code to call these functions must be the correct type.

#### mxArray Functions Using mwSize/mwIndex

mxCalcSingleSubscript	mxCreateSparseLogicalMatrix <sup>2</sup>
mxMalloc	mxCreateStructArray
mxCopyCharacterToPtr <sup>1</sup>	mxCreateStructMatrix



<code>mxCopyComplex16ToPtr<sup>1</sup></code>	<code>mxGetCell</code>
<code>mxCopyComplex8ToPtr<sup>1</sup></code>	<code>mxGetDimensions</code>
<code>mxCopyInteger1ToPtr<sup>1</sup></code>	<code>mxGetElementSize</code>
<code>mxCopyInteger2ToPtr<sup>1</sup></code>	<code>mxGetField</code>
<code>mxCopyInteger4ToPtr<sup>1</sup></code>	<code>mxGetFieldByNumber</code>
<code>mxCopyPtrToCharacter<sup>1</sup></code>	<code>mxGetIr</code>
<code>mxCopyPtrToComplex16<sup>1</sup></code>	<code>mxGetJc</code>
<code>mxCopyPtrToComplex8<sup>1</sup></code>	<code>mxGetM</code>
<code>mxCopyPtrToInteger1<sup>1</sup></code>	<code>mxGetN</code>
<code>mxCopyPtrToInteger2<sup>1</sup></code>	<code>mxGetNumberOfDimensions</code>
<code>mxCopyPtrToInteger4<sup>1</sup></code>	<code>mxGetNumberOfElements</code>
<code>mxCopyPtrToPtrArray<sup>1</sup></code>	<code>mxGetNzmax</code>
<code>mxCopyPtrToReal14<sup>1</sup></code>	<code>mxGetProperty</code>
<code>mxCopyPtrToReal18<sup>1</sup></code>	<code>mxGetString</code>
<code>mxCopyReal14ToPtr<sup>1</sup></code>	<code>mxMalloc</code>
<code>mxCopyReal18ToPtr<sup>1</sup></code>	<code>mxRealloc</code>
<code>mxCreateCellArray</code>	<code>mxSetCell</code>
<code>mxCreateCellMatrix</code>	<code>mxSetDimensions</code>
<code>mxCreateCharArray</code>	<code>mxSetField</code>
<code>mxCreateCharMatrixFromStrings</code>	<code>mxSetFieldByNumber</code>
<code>mxCreateDoubleMatrix</code>	<code>mxSetIr</code>
<code>mxCreateLogicalArray<sup>2</sup></code>	<code>mxSetJc</code>
<code>mxCreateLogicalMatrix<sup>2</sup></code>	<code>mxSetM</code>
<code>mxCreateNumericArray</code>	<code>mxSetN</code>
<code>mxCreateNumericMatrix</code>	<code>mxSetNzmax</code>
<code>mxCreateSparse</code>	<code>mxSetProperty</code>

<sup>1</sup>Fortran function only.

<sup>2</sup>C function only.

Functions in this API use the `mwIndex` and `mwSize` types.

## Building the Binary MEX File

Use the `mex` build script option `-largeArrayDims` with the 64-bit API.

### Example

The example, `arraySize.c` in `matlabroot/extern/examples/mex`, shows memory requirements of large `mxArrays`. To see the example, open the file in MATLAB Editor.

This function requires one positive scalar numeric input, which it uses to create a square matrix. It checks the size of the input to make sure that your system can theoretically create a matrix of this size. If the input is valid, it displays the size of the `mxArray` in kilobytes.

Build this MEX file.

```
mex -largeArrayDims arraySize.c
```

Run the MEX file.

```
arraySize(2^10)
```

```
Dimensions: 1024 x 1024  
Size of array in kilobytes: 1024
```

If your system does not have enough memory to create the array, MATLAB displays an `Out of memory error`.

You can experiment with this function to test the performance and limits of handling large arrays on your system.

### Caution Using Negative Values

When using the 64-bit API, `mwSize` and `mwIndex` are equivalent to `size_t` in C/C++. This type is unsigned, unlike `int`, which is the type used in the 32-bit API. Be careful not to pass any negative values to functions that take `mwSize` or `mwIndex` arguments.

---

Do not cast negative `int` values to `mwSize` or `mwIndex`; the returned value cannot be predicted. Instead, change your code to avoid using negative values.

## Building Cross-Platform Applications

If you develop programs that can run on both 32- and 64-bit architectures, pay attention to the upper limit of values for `mwSize` and `mwIndex`. The 32-bit application reads these values and assigns them to variables declared as `int` in C/C++. Be careful to avoid assigning a large `mwSize` or `mwIndex` value to an `int` or other variable that might be too small.

### See Also

`mex` | `mwIndex` | `mwSize`

## Memory Management

### In this section...

“Automatic Cleanup of Temporary Arrays” on page 5-66

“Example” on page 5-67

“Persistent Arrays” on page 5-67

### Automatic Cleanup of Temporary Arrays

When a MEX file returns control to MATLAB, it returns the results of its computations in the output arguments—the `mxArrays` contained in the left-side arguments `plhs[ ]`. These arrays must have a temporary scope, so do not pass arrays created with the `mexMakeArrayPersistent` function in `plhs`. MATLAB destroys any `mxArray` created by the MEX file that is not in `plhs`. MATLAB also frees any memory that was allocated in the MEX file using the `mxMalloc`, `mxRealloc`, or `mxCalloC` functions.

MathWorks recommends that MEX-file functions destroy their own temporary arrays and free their own dynamically allocated memory. It is more efficient to perform this cleanup in the source MEX-file than to rely on the automatic mechanism. However, there are several circumstances in which the MEX file does not reach its normal return statement.

The normal return is not reached if:

- MATLAB calls `mexErrMsgTxt`.
- MATLAB calls `mexCallMATLAB` and the function being called creates an error. (A source MEX file can trap such errors by using the `mexCallMATLABWithTrap` function, but not all MEX files necessarily need to trap errors.)
- The user interrupts the MEX file execution using **Ctrl+C**.
- The binary MEX file runs out of memory. The MATLAB out-of-memory handler terminates the MEX file.

For the first two cases, a MEX file programmer can ensure safe cleanup of temporary arrays and memory before returning, but not in the last two cases. The automatic cleanup mechanism is necessary to prevent memory leaks in those cases.

You must use the MATLAB-provided functions, such as `mxCalloC` and `mxFree`, to manage memory. Do not use the standard C library counterparts; doing so can produce unexpected results, including program termination.

## Example

This example shows how to allocate memory for variables in a MEX file. For example, if the first input to your function (`prhs[0]`) is a string, in order to manipulate the string, create a buffer `buf` of size `buflen`. The following statements declare these variables:

```
char *buf;  
int buflen;
```

The size of the buffer depends the number of dimensions of your input array and the size of the data in the array. This statement calculates the size of `buflen`:

```
buflen = mxGetN(prhs[0])*sizeof(mxChar)+1;
```

Next, allocate memory for `buf`:

```
buf = mxMalloc(buflen);
```

At the end of the program, if you do not return `buf` as a `plhs` output parameter, then free its memory as follows:

```
mxFree(buf);
```

Before exiting the MEX file, destroy any temporary arrays and free any dynamically allocated memory, except if such an `mxArray` is returned in the output argument list, returned by `mxGetVariablePtr`, or used to create a structure. Also, never delete input arguments.

Use `mxFree` to free memory allocated by the `mxMalloc`, `mxMalloc`, or `mxRealloc` functions. Use `mxDestroyArray` to free memory allocated by the `mxCreate*` functions.

## Persistent Arrays

You can exempt an array, or a piece of memory, from the MATLAB automatic cleanup by calling `mxMakeArrayPersistent` or `mxMakeMemoryPersistent`. However, if a MEX file creates such persistent objects, there is a danger that a memory leak could occur if the MEX file is cleared before the persistent object is properly destroyed. To prevent memory leaks, use the `mxAtExit` function to register a function to free the memory for objects created using these functions.

For example, here is a source MEX file that creates a persistent array and properly disposes of it.

```
#include "mex.h"

static int initialized = 0;
static mxArray *persistent_array_ptr = NULL;

void cleanup(void) {
    mexPrintf("MEX file is terminating, destroying array\n");
    mxDestroyArray(persistent_array_ptr);
}

void mexFunction(int nlhs,
                 mxArray *plhs[],
                 int nrhs,
                 const mxArray *prhs[])
{
    if (!initialized) {
        mexPrintf("MEX file initializing, creating array\n");

        /* Create persistent array and register its cleanup. */
        persistent_array_ptr = mxCreateDoubleMatrix(1, 1, mxREAL);
        mexMakeArrayPersistent(persistent_array_ptr);
        mexAtExit(cleanup);
        initialized = 1;

        /* Set the data of the array to some interesting value. */
        *mxGetPr(persistent_array_ptr) = 1.0;
    } else {
        mexPrintf("MEX file executing; value of first array element is %g\n",
                 *mxGetPr(persistent_array_ptr));
    }
}
```

## See Also

[mexAtExit](#) | [mexMakeArrayPersistent](#) | [mxMalloc](#) | [mxFree](#)

## More About

- “How MATLAB Allocates Memory”
- “Memory Management Issues” on page 4-65

## Handling Large File I/O

### In this section...

- “Prerequisites to Using 64-Bit I/O” on page 5-69
- “Specifying Constant Literal Values” on page 5-71
- “Opening a File” on page 5-71
- “Printing Formatted Messages” on page 5-72
- “Replacing `fseek` and `ftell` with 64-Bit Functions” on page 5-72
- “Determining the Size of an Open File” on page 5-73
- “Determining the Size of a Closed File” on page 5-74

### Prerequisites to Using 64-Bit I/O

MATLAB supports the use of 64-bit file I/O operations in your MEX file programs. You can read and write data to files that are up to and greater than 2 GB ( $2^{31-1}$  bytes) in size. Some operating systems or compilers do not support files larger than 2 GB. The following topics describe how to use 64-bit file I/O in your MEX files.

- “Header File” on page 5-69
- “Type Declarations” on page 5-69
- “Functions” on page 5-70

#### Header File

Header file `io64.h` defines many of the types and functions required for 64-bit file I/O. The statement to include this file must be the *first* `#include` statement in your source file and must also precede any system header include statements:

```
#include "io64.h"
#include "mex.h"
```

#### Type Declarations

To declare variables used in 64-bit file I/O, use the following types.

MEX Type	Description	POSIX
<code>fpos_t</code>	Declares a 64-bit <code>int</code> type for <code>setFilePos()</code> and	<code>fpos_t</code>

MEX Type	Description	POSIX
	<code>getFilePos()</code> . Defined in <code>io64.h</code> .	
<code>int64_T</code> , <code>uint64_T</code>	Declares 64-bit signed and unsigned integer types. Defined in <code>tmwtypes.h</code> .	<code>long</code> , <code>long</code>
<code>structStat</code>	Declares a structure to hold the size of a file. Defined in <code>io64.h</code> .	<code>struct stat</code>
<code>FMT64</code>	Used in <code>mexPrintf</code> to specify length within a format specifier such as <code>%d</code> . See example in the section “Printing Formatted Messages” on page 5-72. <code>FMT64</code> is defined in <code>tmwtypes.h</code> .	<code>%lld</code>
<code>LL</code> , <code>LLU</code>	Suffixes for literal <code>int</code> constant 64-bit values (C Standard ISO <sup>®</sup> /IEC 9899:1999(E) Section 6.4.4.1). Used only on UNIX systems.	<code>LL</code> , <code>LLU</code>

### Functions

Use the following functions for 64-bit file I/O. All are defined in the header file `io64.h`.

Function	Description	POSIX
<code>fileno()</code>	Gets a file descriptor from a file pointer	<code>fileno()</code>
<code>fopen()</code>	Opens the file and obtains the file pointer	<code>fopen()</code>
<code>getFileFstat()</code>	Gets the file size of a given file pointer	<code>fstat()</code>
<code>getFilePos()</code>	Gets the file position for the next I/O	<code>fgetpos()</code>
<code>getFileStat()</code>	Gets the file size of a given file name	<code>stat()</code>
<code>setFilePos()</code>	Sets the file position for the next I/O	<code>fsetpos()</code>



## Specifying Constant Literal Values

To assign signed and unsigned 64-bit integer literal values, use type definitions `int64_T` and `uint64_T`.

On UNIX systems, to assign a literal value to an integer variable where the value to be assigned is greater than  $2^{31} - 1$  signed, you must suffix the value with `LL`. If the value is greater than  $2^{32} - 1$  unsigned, then use `LLU` as the suffix. These suffixes are not valid on Microsoft Windows systems.

---

**Note:** The `LL` and `LLU` suffixes are not required for hardcoded (literal) values less than  $2^{31} - 1$ , even if they are assigned to a 64-bit `int` type.

---

The following example declares a 64-bit integer variable initialized with a large literal `int` value, and two 64-bit integer variables:

```
void mexFunction(int nlhs, mxArray *plhs[], int nrhs,
                 const mxArray *prhs[])
{
    #if defined(_MSC_VER) || defined(__BORLANDC__)    /* Windows */
        int64_T large_offset_example = 9000222000;
    #else                                           /* UNIX */
        int64_T large_offset_example = 9000222000LL;
    #endif

    int64_T offset = 0;
    int64_T position = 0;
}
```

## Opening a File

To open a file for reading or writing, use the C/C++ `fopen` function as you normally would. As long as you have included `io64.h` at the start of your program, `fopen` works correctly for large files. No changes at all are required for `fread`, `fwrite`, `fprintf`, `fscanf`, and `fclose`.

The following statements open an existing file for reading and updating in binary mode.

```
fp = fopen(filename, "r+b");
if (NULL == fp)
```

```
{
/* File does not exist. Create new file for writing
 * in binary mode.
 */
fp = fopen(filename, "wb");
if (NULL == fp)
    {
    sprintf(str, "Failed to open/create test file '%s'",
            filename);
    mexErrMsgTxt(str);
    return;
    }
else
    {
    mexPrintf("New test file '%s' created\n",filename);
    }
}
else mexPrintf("Existing test file '%s' opened\n",filename);
```

## Printing Formatted Messages

You cannot print 64-bit integers using the `%d` conversion specifier. Instead, use `FMT64` to specify the appropriate format for your platform. `FMT64` is defined in the header file `tmwtypes.h`. The following example shows how to print a message showing the size of a large file:

```
int64_T large_offset_example = 9000222000LL;

mexPrintf("Example large file size: %" FMT64 "d bytes.\n",
          large_offset_example);
```

## Replacing `fseek` and `ftell` with 64-Bit Functions

The ANSI C `fseek` and `ftell` functions are not 64-bit file I/O capable on most platforms. The functions `setFilePos` and `getFilePos`, however, are defined as the corresponding POSIX<sup>®</sup> `fsetpos` and `fgetpos` (or `fsetpos64` and `fgetpos64`) as required by your platform/OS. These functions are 64-bit file I/O capable on all platforms.

The following example shows how to use `setFilePos` instead of `fseek`, and `getFilePos` instead of `ftell`. The example uses `getFileFstat` to find the size of the file. It then uses `setFilePos` to seek to the end of the file to prepare for adding data at the end of the file.

---

**Note:** Although the `offset` parameter to `setFilePos` and `getFilePos` is really a pointer to a signed 64-bit integer, `int64_T`, it must be cast to an `fpos_T*`. The `fpos_T` type is defined in `io64.h` as the appropriate `fpos64_t` or `fpos_t`, as required by your platform OS.

---

```
getFileFstat(fileno(fp), &statbuf);
fileSize = statbuf.st_size;
offset = fileSize;

setFilePos(fp, (fpos_T*) &offset);
getFilePos(fp, (fpos_T*) &position );
```

Unlike `fseek`, `setFilePos` supports only absolute seeking relative to the beginning of the file. If you want to do a relative seek, first call `getFileFstat` to obtain the file size. Then convert the relative offset to an absolute offset that you can pass to `setFilePos`.

## Determining the Size of an Open File

To get the size of an open file:

- Refresh the record of the file size stored in memory using `getFilePos` and `setFilePos`.
- Retrieve the size of the file using `getFileFstat`.

### Refreshing the File Size Record

Before attempting to retrieve the size of an open file, first refresh the record of the file size residing in memory. If you skip this step on a file that is opened for writing, the file size returned might be incorrect or 0.

To refresh the file size record, seek to any offset in the file using `setFilePos`. If you do not want to change the position of the file pointer, you can seek to the current position in the file. This example obtains the current offset from the start of the file. It then seeks to the current position to update the file size without moving the file pointer.

```
getFilePos( fp, (fpos_T*) &position);
setFilePos( fp, (fpos_T*) &position);
```

### Getting the File Size

The `getFileFstat` function takes a file descriptor input argument. Use `fileno` function to get the file pointer of the open file. `getFileFstat` returns the size of that file in bytes in the `st_size` field of a `structStat` structure.

```
structStat statbuf;
int64_T fileSize = 0;

if (0 == getFileFstat(fileno(fp), &statbuf))
{
    fileSize = statbuf.st_size;
    mexPrintf("File size is %" FMT64 "d bytes\n", fileSize);
}
```

### Determining the Size of a Closed File

The `getFileStat` function takes the file name of a closed file as an input argument. `getFileStat` returns the size of the file in bytes in the `st_size` field of a `structStat` structure.

```
structStat statbuf;
int64_T fileSize = 0;

if (0 == getFileStat(filename, &statbuf))
{
    fileSize = statbuf.st_size;
    mexPrintf("File size is %" FMT64 "d bytes\n", fileSize);
}
```

## Install MinGW-w64 Compiler

You can use the MinGW-w64 version 4.9.2 compiler from TDM-GCC to build MEX files and standalone MATLAB engine and MAT-file applications.

To install the compiler, use the Add-Ons menu. Search for MinGW or select from **Features**.

### Building `yprime.c` Example

You can test the MinGW compiler by building the `yprime.c` example. Copy the source file to a writable folder.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'mex', 'yprime.c'), '.', 'f')
```

If you only have the MinGW compiler installed on your system, the `mex` command automatically chooses MinGW. Go to the next step. However, if you have multiple C or C++ compilers, use `mex -setup` to choose MinGW.

```
mex -setup
```

Build the MEX file.

```
mex yprime.c
```

MATLAB displays a “Building with” message showing what compiler was used to build the MEX file.

Run the function.

```
yprime(1,1:4)
```

For more information, see “Troubleshooting and Limitations Compiling C/C++ MEX Files with MinGW-w64” on page 5-77.

### MinGW Installation Folder Cannot Contain Space

Do not install MinGW in a location with spaces in the path name. For example, do not use:

```
C:\Program Files\TDM-GCC-64
```

Instead, use:

C:\TDM-GCC-64

### Updating MEX Files to Use MinGW Compiler

If you have MEX source files built with a different MATLAB-supported compiler, you might need to modify the code in order to build with the MinGW compiler. For example:

- Library (.lib) files generated by Microsoft Visual Studio are not compatible with MinGW.
- Object cleanup is not possible when an exception is thrown using the `mexErrMsgIdAndTxt` function from C++ MEX files, resulting in memory leak.
- An uncaught exception in C++ MEX files compiled with MinGW causes MATLAB to crash.
- MEX files with variables containing large amounts of data cannot be compiled, as the compiler runs out of memory.

### More About

- “Add-Ons”
- “Troubleshooting and Limitations Compiling C/C++ MEX Files with MinGW-w64” on page 5-77

### External Websites

- Supported and Compatible Compilers

# Troubleshooting and Limitations Compiling C/C++ MEX Files with MinGW-w64

## In this section...

“Do Not Link to Library Files Compiled with Non-MinGW Compilers” on page 5-77

“MinGW Installation Folder Cannot Contain Space” on page 5-77

“MEX Command Does not Choose MinGW” on page 5-78

“Manually Configure MinGW for MATLAB” on page 5-78

“MinGW Behaves Similarly to gcc/g++ on Linux” on page 5-79

“Potential Memory Leak Inside C++ MEX Files on Using MEX Exceptions” on page 5-79

“Unhandled Explicit Exceptions in C++ MEX Files Unexpectedly Terminate MATLAB” on page 5-80

“Out of Memory Error for Variables Containing Large Amounts of Data” on page 5-81

## Do Not Link to Library Files Compiled with Non-MinGW Compilers

If you use the MinGW compiler to build a MEX file that links to a library compiled with a non-MinGW compiler, such as Microsoft Visual Studio, the file will not run in MATLAB. Library (.lib) files generated by different compilers are not compatible with each other.

You can generate a new library file using the `dlltool` utility from MinGW.

## MinGW Installation Folder Cannot Contain Space

Do not install MinGW in a location with spaces in the path name. For example, do not use:

```
C:\Program Files\TDM-GCC-64
```

Instead, use:

```
C:\TDM-GCC-64
```

## MEX Command Does not Choose MinGW

If you only have the MinGW compiler installed on your system, the `mex` command automatically chooses MinGW for both C and C++ MEX files. If you have multiple C or C++ compilers, use `mex -setup` to choose MinGW for both C and, if required, C++ MEX files.

```
mex -setup  
mex -setup cpp
```

If you only type `mex -setup` choosing MinGW, when you compile a C++ file, `mex` might choose a different compiler.

## Manually Configure MinGW for MATLAB

MATLAB detects the MinGW compiler by reading an environment variable, `MW_MINGW64_LOC`. When you install MinGW from the MATLAB **Add-Ons** menu, MATLAB sets this variable.

If necessary, you can set this variable globally, if you have Windows administrative privileges, using the Windows Control Panel. Alternatively, set the variable every time you open MATLAB.

---

**Note:** Verify you have installed MinGW-w64 version 4.9.2 before setting the environment variable.

---

### Set variable using Windows Control Panel

To set the environment variable on Windows 7:

- 1 Make sure you have administrative privileges.
- 2 Select **Computer** from the Start menu.
- 3 Choose **System properties** from the context menu.
- 4 Click **Advanced system settings > Advanced** tab.
- 5 Click **Environment Variables**.
- 6 Under **System variables**, select **New**.
- 7 In the **New System Variable** dialog box, type `MW_MINGW64_LOC` in the **Variable name** field.



- 8 In the **Variable value** field, type the location of the MinGW-w64 compiler installation, for example, `C:\TDM-GCC-64`.
- 9 Click **Ok** to close the dialog boxes, then close the **Control Panel** dialog box.

### Set variable for MATLAB session

To set the environment variable in MATLAB, type:

```
setenv('MW_MINGW64_LOC', folder)
```

where *folder* is the installation directory, for example, `'C:\TDM-GCC-64'`. You must set the variable every time you run MATLAB.

## MinGW Behaves Similarly to gcc/g++ on Linux

When modifying compiler flags using the `mex` command, use the Linux compiler flags `CFLAGS` or `CXXFLAGS` instead of the Windows flag `COMPFLAGS`.

## Potential Memory Leak Inside C++ MEX Files on Using MEX Exceptions

Error handling in C++ MEX files compiled with the MinGW-w64 compiler is not consistent with MATLAB error handling. If a C++ MEX file contains a class, using the `mexErrMsgIdAndTxt` function to throw a MEX exception can cause a memory leak for objects created for the class.

For example, the following C++ MEX function contains class `MyClass`.

```
#include "mex.h"

class MyClass {
public:
    MyClass() {
        mexPrintf("Constructor called");
    }
    ~MyClass() {
        mexPrintf("Destructor called");
    }
};

void mexFunction(int nlhs, mxArray *plhs[], int nrhs, const mxArray *prhs[])
{
    MyClass X;
```

```
    if (nrhs != 0) {
        mexErrMsgIdAndTxt("MATLAB:cppfeature:invalidNumInputs",
                          "No input arguments allowed.");
    }
}
```

The MEX function creates object `X` from `MyClass`, then checks the number of input arguments. If the MEX function calls `mexErrMsgIdAndTxt`, the MATLAB error handling does not free memory for object `X`, thus creating a memory leak.

## Unhandled Explicit Exceptions in C++ MEX Files Unexpectedly Terminate MATLAB

If a function in a C++ MEX file throws an explicit exception which is not caught inside the MEX file with a `catch` statement, then the exception causes MATLAB to terminate instead of propagating the error to the MATLAB command line.

```
#include "mex.h"

class error {}; // Throw an exception of this class

class MyClass
{
public:
    MyClass(){
        mexPrintf("Constructor called.");
    }
    ~MyClass(){
        mexPrintf("Destructor called.");
    }
};

void doErrorChecking(const MyClass& obj)
{
    // Do error checking
    throw error();
}

void createMyClass()
{
    MyClass myobj;
    doErrorChecking(myobj);
}
```

```

}

void mexFunction(int nlhs, mxArray *plhs[], int nrhs, const mxArray *prhs[])
{
    createMyClass();
}

```

The MEX function calls `createMyClass`, which creates an object of class `MyClass` and calls function `doErrorChecking`. Function `doErrorChecking` throws an exception of type `error`. This exception, however, is not caught inside the MEX file and causes MATLAB to crash.

This behavior also occurs for classes inheriting from the class `std::exception`.

### Work around

Catch the exception in the MEX function:

```

void mexFunction(int nlhs, mxArray *plhs[], int nrhs, const mxArray *prhs[])
{
    try{
        createMyClass();
    }
    catch(error e){
        // Error handling
    }
}

```

## Out of Memory Error for Variables Containing Large Amounts of Data

The TDM-GCC MinGW 4.9.2 compiler cannot allocate memory for variables in MEX files that contain large amounts of data. The compiler displays an error message like:

```
out of memory allocating XXXXXX bytes
```

### See Also

`mexErrMsgIdAndTxt`



# Fortran MEX-Files

---

- “Components of Fortran MEX File” on page 6-2
- “MATLAB Fortran API Libraries” on page 6-5
- “Data Flow in Fortran MEX Files” on page 6-8
- “User Messages” on page 6-11
- “Error Handling” on page 6-12
- “Build Fortran MEX File” on page 6-13
- “Create Fortran Source MEX File” on page 6-14
- “Set Up Fortran Examples” on page 6-19
- “Pass Scalar Values” on page 6-20
- “Pass Strings” on page 6-21
- “Pass Arrays of Strings” on page 6-22
- “Pass Matrices” on page 6-23
- “Pass Integers” on page 6-24
- “Pass Multiple Inputs or Outputs” on page 6-25
- “Handle Complex Data” on page 6-26
- “Dynamically Allocate Memory” on page 6-27
- “Handle Sparse Matrices” on page 6-28
- “Call MATLAB Functions from Fortran MEX Files” on page 6-29
- “Debug Fortran Source MEX-Files” on page 6-31
- “Handling Large mxArray” on page 6-34
- “Memory Management” on page 6-37
- “MATLAB Supports Fortran 77” on page 6-38

## Components of Fortran MEX File

### In this section...

“mexFunction Gateway Routine” on page 6-2

“Naming the MEX File” on page 6-2

“Difference Between .f and .F Files” on page 6-2

“Required Parameters” on page 6-3

“Managing Input and Output Parameters” on page 6-3

“Validating Inputs” on page 6-4

“Computational Routine” on page 6-4

### mexFunction Gateway Routine

The *gateway routine* is the entry point to the MEX file. It is through this routine that MATLAB accesses the rest of the routines in your MEX files. The name of the gateway routine is `mexFunction`. It takes the place of the main program in your source code.

### Naming the MEX File

The name of the source file containing `mexFunction` is the name of your MEX file, and, hence, the name of the function you call in MATLAB. Name your Fortran source file with an uppercase `.F` file extension.

The file extension of the binary MEX file is platform-dependent. You find the file extension using the `mexext` function, which returns the value for the current machine.

### Difference Between .f and .F Files

To ensure that your Fortran MEX file is platform independent, use an uppercase `.F` file extension.

Fortran compilers assume source files using a lowercase `.f` file extension have been preprocessed. On most platforms, `mex` makes sure that the file is preprocessed regardless of the file extension. However, on Apple Macintosh platforms, `mex` cannot force preprocessing.

## Required Parameters

The Fortran signature for `mexfunction` is:

```
subroutine mexFunction(nlhs, plhs, nrhs, prhs)
integer nlhs, nrhs
mwpointer plhs(*), prhs(*)
```

Place this subroutine after your computational routine and any other subroutines in your source file.

The following table describes the parameters for `mexFunction`.

Parameter	Description
<code>prhs</code>	Array of right-side input arguments.
<code>plhs</code>	Array of left-side output arguments.
<code>nrhs</code>	Number of right-side arguments, or the size of the <code>prhs</code> array.
<code>nlhs</code>	Number of left-side arguments, or the size of the <code>plhs</code> array.

Declare `prhs` and `plhs` as type `mwpointer`, which means they point to MATLAB arrays. They are vectors that contain pointers to the arguments of the MEX file.

You can think of the name `prhs` as representing the “parameters, right-hand side,” that is, the input parameters. Likewise, `plhs` represents the “parameters, left side,” or output parameters.

## Managing Input and Output Parameters

Input parameters (found in the `prhs` array) are read-only; do not modify them in your MEX file. Changing data in an input parameter can produce undesired side effects.

You also must take care when using an input parameter to create output data or any data used locally in your MEX file. If you want to copy an input array into an output array, for example `plhs(1)`, call the `mxDuplicateArray` function to make a copy of the input array. For example:

```
plhs(1) = mxDuplicateArray(prhs(1))
```

For more information, see the troubleshooting topic “Incorrectly Constructing a Cell or Structure `mxAarray`” on page 4-66.

## Validating Inputs

For a list of functions to validate inputs to your subroutines, see the Matrix Library category, “Validate Data”. The `mxIsClass` function is a general-purpose way to test an `mxArray`.

## Computational Routine

The *computational routine* contains the code for performing the computations you want implemented in the binary MEX file. Although not required, consider writing the gateway routine, `mexFunction`, to call a computational routine. To validate input parameters and to convert them into the types required by the computational routine, use the `mexFunction` code as a wrapper.

If you write separate gateway and computational routines, you can combine them into one source file or into separate files. If you use separate files, the file containing `mexFunction` must be the first source file listed in the `mex` command.

## See Also

`mexext` | `mexFunction` | `mwPointer` | `mxDuplicateArray` | `mxIsClass`



## MATLAB Fortran API Libraries

### In this section...

“Matrix Library” on page 6-5

“MEX Library” on page 6-5

“Preprocessor Macros” on page 6-5

“Using the Fortran %val Construct” on page 6-6

The Matrix Library and the MEX Library describe functions you can use in your gateway and computational routines that interact with MATLAB programs and the data in the MATLAB workspace. These libraries are part of the MATLAB C/C++ and Fortran API Reference library.

To use these functions, include the `fintrf` header, which declares the entry point and interface routines. The file is in your `matlabroot\extern\include` folder. Put this statement in your source file:

```
#include "fintrf.h"
```

### Matrix Library

Use Fortran Matrix Library functions to pass `mxArray`, the type MATLAB uses to store arrays, to and from MEX files. For examples using these functions, see `matlabroot/extern/examples/mx`.

### MEX Library

Use MEX Library functions to perform operations in the MATLAB environment. For examples using these functions, see `matlabroot/extern/examples/mex`.

Unlike MATLAB functions, MEX file functions do not have their own variable workspace. MEX file functions operate in the caller workspace. To evaluate a string, use `mexEvalString`. To get and put variables into the caller workspace, use the `mexGetVariable` and `mexPutVariable` functions.

### Preprocessor Macros

The Matrix and MEX libraries use the MATLAB *preprocessor macros* `mwSize` and `mwIndex` for cross-platform flexibility. `mwSize` represents size values, such as array

dimensions and number of elements. `mwIndex` represents index values, such as indices into arrays.

MATLAB has an extra preprocessor macro for Fortran files, `mwPointer`. MATLAB uses a unique data type, the `mxArray`. Because you cannot create a data type in Fortran, MATLAB passes a special identifier, created by the `mwPointer` preprocessor macro, to a Fortran program. This is how you get information about an `mxArray` in a native Fortran data type. For example, you can find out the size of the `mxArray`, determine whether it is a string, and look at the contents of the array. Use `mwPointer` to build platform-independent code.

The Fortran preprocessor converts `mwPointer` to `integer*4` when building binary MEX files on 32-bit platforms and to `integer*8` when building on 64-bit platforms.

---

**Note:** Declaring a pointer to be the incorrect size might cause your program to crash.

---

## Using the Fortran `%val` Construct

The Fortran `%val(arg)` construct specifies that an argument, *arg*, is to be passed by value, instead of by reference. Most, but not all, Fortran compilers support the `%val` construct.

If your compiler does not support the `%val` construct, copy the array values into a temporary true Fortran array using the `mxCopy*` routines (for example, `mxCopyPtrToReal8`).

### `%val` Construct Example

If your compiler supports the `%val` construct, you can use routines that point directly to the data (that is, the pointer returned by `mxGetPr` or `mxGetPi`). You can use `%val` to pass the contents of this pointer to a subroutine, where it is declared as a Fortran double-precision matrix.

For example, consider a gateway routine that calls its computational routine, `yprime`, by:

```
call yprime(%val(y), %val(t), %val(y))
```

If your Fortran compiler does not support the `%val` construct, you would replace the call to the computational subroutine with:

```
C Copy array pointers to local arrays.  
    call mxCopyPtrToReal8(t, tr, 1)  
    call mxCopyPtrToReal8(y, yr, 4)  
C  
C Call the computational subroutine.  
    call yprime(ypr, tr, yr)  
C  
C Copy local array to output array pointer.  
    call mxCopyReal8ToPtr(ypr, yp, 4)
```

You must also add the following declaration line to the top of the gateway routine:

```
real*8 ypr(4), tr, yr(4)
```

If you use `mxCopyPtrToReal8` or any of the other `mxCopy*` routines, the size of the arrays declared in the Fortran gateway routine must be greater than or equal to the size of the inputs to the MEX file coming in from MATLAB. Otherwise, `mxCopyPtrToReal8` does not work correctly.

## See Also

“Fortran Matrix Library API” | “MEX Library API” | `mwIndex` | `mwPointer` | `mwSize`  
| `mxArray`

## Data Flow in Fortran MEX Files

### In this section...

“Showing Data Input and Output” on page 6-8

“Gateway Routine Data Flow Diagram” on page 6-9

### Showing Data Input and Output


Suppose your MEX-file `myFunction` has two input arguments and one output argument. The MATLAB syntax is `[X] = myFunction(Y, Z)`. To call `myFunction` from MATLAB, type:

```
X = myFunction(Y, Z);
```

The MATLAB interpreter calls `mexFunction`, the gateway routine to `myFunction`, with the following arguments:

```
nlhs = 1
```

```
nrhs = 2
```



Your input is `prhs`, a two-element array (`nrhs = 2`). The first element is a pointer to an `mxAarray` named `Y` and the second element is a pointer to an `mxAarray` named `Z`.

Your output is `plhs`, a one-element array (`nlhs = 1`) where the single element is a `null` pointer. The parameter `plhs` points at nothing because the output `X` is not created until the subroutine executes.

The gateway routine creates the output array and sets a pointer to it in `plhs[0]`. If the routine does not assign a value to `plhs[0]` but you assign an output value to the function when you call it, MATLAB generates an error.

---

**Note:** It is possible to return an output value even if `nlhs = 0`, which corresponds to returning the result in the `ans` variable.

---


## Gateway Routine Data Flow Diagram

The following MEX Cycle diagram shows how inputs enter a MEX-file, what functions the gateway routine performs, and how outputs return to MATLAB.

In this example, the syntax of the MEX-file `func` is `[C, D] = func(A,B)`. In the figure, a call to `func` tells MATLAB to pass variables `A` and `B` to your MEX-file. `C` and `D` are left unassigned.

The gateway routine uses the `mxCreate*` functions to create the MATLAB arrays for your output arguments. It sets `plhs[0]` and `plhs[1]` to the pointers to the newly created MATLAB arrays. It uses the `mxGet*` functions to extract your data from your input arguments `prhs[0]` and `prhs[1]`. Finally, it calls your computational routine, passing the input and output data pointers as function parameters.

MATLAB assigns `plhs[0]` to `C` and `plhs[1]` to `D`.



**Fortran MEX Cycle**

## User Messages

To print text in the MATLAB Command Window, use the `mexPrintf` function. To print error and warning information in the Command Window, use the `mexErrMsgIdAndTxt` and `mexWarnMsgIdAndTxt` functions.

For example, the following code snippet displays an error message.

```
parameter(maxbuf = 100)
character*100 input_buf

if (status = mxGetString(prhs(1), input_buf, maxbuf) .ne. 0) then
    call mexErrMsgIdAndTxt ('MATLAB:myfunc:readError',
+                          'Error reading string.')
endif
```

### See Also

[mexErrMsgIdAndTxt](#) | [mexPrintf](#) | [mexWarnMsgIdAndTxt](#)

## Error Handling

The `mexErrMsgIdAndTxt` function prints error information and terminates your binary MEX file. For an example, see the following code in `matlabroot/extern/examples/mx/mxcreatecellmatrixf.F`.

```
C      Check for proper number of input and output arguments
      if (nrhs .lt. 1) then
          call mexErrMsgIdAndTxt( 'MATLAB:mxcreatecellmatrixf:minrhs',
+          'One input argument required.')
      end if
```

The `mexWarnMsgIdAndTxt` function prints information, but does not terminate the MEX file. For an example, see the following code in `matlabroot/extern/examples/mx/mxgetepsf.F`.

```
C      Check for equality within eps
      do 20 j=1,elements
          if ((abs(first(j) - second(j))).gt.(abs(second(j)*eps))) then
              call mexWarnMsgIdAndTxt(
+              'MATLAB:mxgetepsf:NotEqual',
+              'Inputs are not the same within eps.')
              go to 21
          end if
      20 continue
```

### See Also

`mexErrMsgIdAndTxt` | `mexWarnMsgIdAndTxt`

### Related Examples

- `mxcreatecellmatrixf.F`
- `mxgetepsf.F`



## Build Fortran MEX File

This example shows how to build the example MEX file, `timestwo`. Use this example to verify the build configuration for your system.

To build a code example, first copy the file to a writable folder, such as `c:\work`, on your path:

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'refbook', 'timestwo.F'), '.', 'f')
```

Use the `mex` command to build the MEX file.

```
mex timestwo.F
```

This command creates the file `timestwo.ext`, where `ext` is the value returned by the `mexext` function.

The `timestwo` function takes a scalar input and doubles it. Call `timestwo` as if it were a MATLAB function.

```
timestwo(4)
ans =
     8
```

### See Also

[mex](#) | [mexext](#)

### More About

- “Handling Large mxArray’s” on page 5-62
- “Upgrade MEX Files to Use 64-Bit API” on page 4-35

## Create Fortran Source MEX File

This example shows how to write a MEX file to call a Fortran subroutine, `timestwo`, in MATLAB using a MATLAB matrix.

`timestwo` multiplies an  $n$ -dimensional array, `x_input`, by 2, and returns the results in array, `y_output`.

```
subroutine timestwo(y_output, x_input)
  real*8 x_input, y_output

  y_output = 2.0 * x_input
  return
end
```

### Create Source File

Open MATLAB Editor, create a file, and document the MEX file with the following information.

```
C=====
C   timestwo.f
C   Computational function that takes a scalar and doubles it.
C   This is a MEX file for MATLAB.
C=====
```

Add the Fortran header file, `fintrf.h`, containing the MATLAB API function declarations.

```
#include "fintrf.h"
```

Save the file on your MATLAB path, for example, in `c:\work`, and name it `timestwo.F`. The name of your MEX file is `timestwo`.

### Create Gateway Routine

MATLAB uses the gateway routine, `mexfunction`, as the entry point to a Fortran subroutine. Add the following `mexFunction` code.

```
C   Gateway routine
C   subroutine mexFunction(nlhs, plhs, nrhs, prhs)

C   Declarations
```

```
C    Statements
```

```
    return
    end
```

Add the following statement to your `mexfunction` subroutine to force you to declare all variables.

```
implicit none
```

Explicit type declaration is necessary for 64-bit arrays.

### Declare `mexfunction` Arguments

To declare `mxArray` variables, use the MATLAB type, `mwPointer`. Add this code after the `Declarations` statement.

```
C    mexFunction arguments:
    mwPointer plhs(*), prhs(*)
    integer nlhs, nrhs
```

### Declare Functions and Local Variables

- Declare the symbolic names and types of MATLAB API functions used in this MEX file.

```
C    Function declarations:
    mwPointer mxGetPr
    mwPointer mxCreateDoubleMatrix
    integer mxIsNumeric
    mwPointer mxGetM, mxGetN
```

To determine the type of a function, refer to the MATLAB API function reference documentation. For example, see the documentation for `mxGetPr`.

- Declare local variables for the `mexfunction` arguments.

```
C    Pointers to input/output mxArray:
    mwPointer x_ptr, y_ptr
```

- Declare matrix variables.

```
C    Array information:
    mwPointer mrows, ncols
    mwSize size
```

### Verify MEX File Input and Output Arguments

Verify the number of MEX file input and output arguments using the `nrhs` and `nlhs` arguments. Add these statements to the `mexfunction` code block.

```
C    Check for proper number of arguments.
      if(nrhs .ne. 1) then
        call mexErrMsgIdAndTxt ('MATLAB:timestwo:nInput',
+                               'One input required.')
      elseif(nlhs .gt. 1) then
        call mexErrMsgIdAndTxt ('MATLAB:timestwo:nOutput',
+                               'Too many output arguments.')
      endif
```

Verify the input argument type using the `prhs` argument.

```
C    Check that the input is a number.
      if(mxIsNumeric(prhs(1)) .eq. 0) then
        call mexErrMsgIdAndTxt ('MATLAB:timestwo:NonNumeric',
+                               'Input must be a number.')
      endif
```

### Create Computational Routine

Add the `timestwo` code. This subroutine is your computational routine, the source code that performs the functionality you want to use in MATLAB.

```
C    Computational routine

      subroutine timestwo(y_output, x_input)
      real*8 x_input, y_output

      y_output = 2.0 * x_input
      return
      end
```

A computational routine is optional. Alternatively, you can place the code within the `mexfunction` function block.

### Declare Variables for Computational Routine

Put the following variable declarations in `mexFunction`.

```
C    Arguments for computational routine:
```

```
real*8 x_input, y_output
```

### Read Input Array

To point to the input matrix data, use the `mxGetPr` function.

```
x_ptr = mxGetPr(prhs(1))
```

To create a Fortran array, `x_input`, use the `mxCopyPtrToReal8` function.

```
C    Get the size of the input array.
    mrows = mxGetM(prhs(1))
    ncols = mxGetN(prhs(1))
    size = mrows*ncols

C    Create Fortran array from the input argument.
    call mxCopyPtrToReal8(x_ptr,x_input,size)
```

### Prepare Output Data

To create the output argument, `plhs(1)`, use the `mxCreateDoubleMatrix` function.

```
C    Create matrix for the return argument.
    plhs(1) = mxCreateDoubleMatrix(mrows,ncols,0)
```

Use the `mxGetPr` function to assign the `y_ptr` argument to `plhs(1)`.

```
y_ptr = mxGetPr(plhs(1))
```

### Perform Calculation

Pass the arguments to `timestwo`.

```
C    Call the computational subroutine.
    call timestwo(y_output, x_input)
```

### Copy Results to Output Argument

```
C    Load the data into y_ptr, which is the output to MATLAB.
    call mxCopyReal8ToPtr(y_output,y_ptr,size)
```

### View Complete Source File

Compare your source file with `timestwo.F`, located in the `matlabroot/extern/examples/refbook` folder. Open the file in the editor.

### Build Binary MEX File

At the MATLAB command prompt, build the binary MEX file.

```
mex timestwo.F
```

### Test the MEX File

```
x = 99;  
y = timestwo(x)
```

```
y =  
    198
```

### See Also

[mexfunction](#) | [mwPointer](#) | [mwSize](#) | [mxCreateDoubleMatrix](#) | [mxGetM](#) | [mxGetN](#)  
| [mxGetPr](#) | [mxIsNumeric](#)

### Related Examples

- [timestwo.F](#)

## Set Up Fortran Examples

The “Fortran Matrix Library API” provides a set of Fortran routines that handle the types supported by MATLAB. For each data type, there is a specific set of functions that you can use for data manipulation.

Source code for Fortran examples is located in the *matlabroot/extern/examples/refbook* folder of your MATLAB installation. To build an example, first copy the file to a writable folder, such as *c:\work*, on your path:

```
copyfile(fullfile(matlabroot,'extern','examples','refbook','filename.F'),'.','f')
```

where *filename* is the name of the example.

Make sure that you have a Fortran compiler installed. Then, at the MATLAB command prompt, type:

```
mex filename.F
```

where *filename* is the name of the example.

This section looks at source code for the examples. Unless otherwise specified, the term “MEX file” refers to a source file.

For a list of MEX example files available with MATLAB, see “Table of MEX File Source Code Files” on page 5-24.

## Pass Scalar Values

Here is a Fortran computational routine that takes a scalar and doubles it.

```
      subroutine timestwo(y, x)
      real*8 x, y
C
      y = 2.0 * x
      return
      end
```

To see the same function written in the MEX file format (`timestwo.F`), open the file in MATLAB Editor.

To build this example, at the command prompt type:

```
mex timestwo.F
```

This command creates the binary MEX file called `timestwo` with an extension corresponding to the machine type on which you are running. You can now call `timestwo` like a MATLAB function:

```
x = 2;
y = timestwo(x)

y =
     4
```



## Pass Strings

Passing strings from MATLAB to a Fortran MEX file is straightforward. The program `revord.F` accepts a string and returns the characters in reverse order. To see the example `revord.F`, open the file in MATLAB Editor.

After checking for the correct number of inputs, the gateway routine `mexFunction` verifies that the input was a row vector string. It then finds the size of the string and places the string into a Fortran character array. For character strings, it is not necessary to copy the data into a Fortran character array using `mxCopyPtrToCharacter`. (`mxCopyPtrToCharacter` is a convenience function for working with MAT-files.)

To build this example, at the command prompt type:

```
mex revord.F
```

Type:

```
x = 'hello world';  
y = revord(x)
```

```
y =
```

```
dlrow olleh
```

## Pass Arrays of Strings

Passing arrays of strings adds a complication to the example “Pass Strings” on page 6-21. Because MATLAB stores elements of a matrix by column instead of by row, the size of the string array must be correctly defined in the Fortran MEX file. The key point is that the row and column sizes as defined in MATLAB must be reversed in the Fortran MEX file. So, when returning to MATLAB, the output matrix must be transposed.

This example places a string array/character matrix into MATLAB as output arguments rather than placing it directly into the workspace.

To build this example, at the command prompt type:

```
mex passstr.F
```

Type:

```
passstr
```

to create the 5-by-15 `mystring` matrix. You need to do some further manipulation. The original string matrix is 5-by-15. Because of the way MATLAB reads and orients elements in matrices, the size of the matrix must be defined as `M=15` and `N=5` in the MEX file. After the matrix is put into MATLAB, the matrix must be transposed. The program `passstr.F` illustrates how to pass a character matrix. To see the code `passstr.F`, open the file in MATLAB Editor.

Type:

```
passstr
```

```
ans =
```

```
MATLAB  
The Scientific  
Computing  
Environment  
by TMM, Inc.
```

## Pass Matrices

In MATLAB, you can pass matrices into and out of MEX files written in Fortran. You can manipulate the MATLAB arrays by using `mxGetPr` and `mxGetPi` to assign pointers to the real and imaginary parts of the data stored in the MATLAB arrays. You can create MATLAB arrays from within your MEX file by using `mxCreateDoubleMatrix`.

The example `matsq.F` takes a real 2-by-3 matrix and squares each element. To see the source code, open the file in MATLAB Editor.

After performing error checking to ensure that the correct number of inputs and outputs was assigned to the gateway subroutine and to verify the input was in fact a numeric matrix, `matsq.F` creates a matrix. The matrix is copied to a Fortran matrix using `mxCopyPtrToReal8`. Now the computational subroutine can be called, and the return argument is placed into `y_ptr`, the pointer to the output, using `mxCopyReal8ToPtr`.

To build this example, at the command prompt type:

```
mex matsq.F
```

For a 2-by-3 real matrix, type:

```
x = [1 2 3; 4 5 6];  
y = matsq(x)
```

```
y =  
    1     4     9  
   16    25    36
```

### See Also

`mxCreateDoubleMatrix` | `mxGetPi` | `mxGetPr`

## Pass Integers

The example `matsqint8.F` accepts a matrix of MATLAB type `int8` and squares each element. To see the source code, open the file in MATLAB Editor. Data of type `int8`, a signed 8-bit integer, is equivalent to Fortran type `integer*1`, a signed 1-byte integer. To copy values between MATLAB and Fortran arrays, use the `mxCopyPtrToInteger1` and `mxCopyInteger1ToPtr` functions.

To build this example, at the command prompt type:

```
mex matsqint8.F
```

Type:

```
B = int8([1 2; 3 4; -5 -6]);  
y = matsqint8(B)
```

```
y =  
    1     4  
    9    16  
   25    36
```

For information about using other integer data types, consult your Fortran compiler manual.

### See Also

`mxCopyInteger1ToPtr` | `mxCopyPtrToInteger1`

## Pass Multiple Inputs or Outputs

The `plhs` and `prhs` parameters (see “Components of Fortran MEX File” on page 6-2) are vectors containing pointers to the left side (output) variables and right-hand side (input) variables. `plhs(1)` contains a pointer to the first left side argument, `plhs(2)` contains a pointer to the second left side argument, and so on. Likewise, `prhs(1)` contains a pointer to the first right-hand side argument, `prhs(2)` points to the second, and so on.

The example `xtimesy.F` multiplies an input scalar times an input scalar or matrix. To see the source code, open the file in MATLAB Editor.

As this example shows, creating MEX file gateways that handle multiple inputs and outputs is straightforward. Keep track of which indices of the vectors `prhs` and `plhs` correspond to which input and output arguments of your function. In this example, the input variable `x` corresponds to `prhs(1)` and the input variable `y` to `prhs(2)`.

To build this example, at the command prompt type:

```
mex xtimesy.F
```

For an input scalar `x` and a real 3-by-3 matrix, type:

```
x = 3;  
y = ones(3);  
z = xtimesy(x, y)
```

```
z =  
    3     3     3  
    3     3     3  
    3     3     3
```

## Handle Complex Data

MATLAB stores complex double-precision data as two vectors of numbers—one vector contains the real data and the other contains the imaginary data. The functions `mxCopyPtrToComplex16` and `mxCopyComplex16ToPtr` copy MATLAB data to a native `complex*16` Fortran array.

The example `convec.F` takes two complex vectors (of length 3) and convolves them. To see the source code, open the file in MATLAB Editor.

To build this example, at the command prompt type:

```
mex convec.F
```

Enter the following at the command prompt:

```
x = [3 - 1i, 4 + 2i, 7 - 3i];  
y = [8 - 6i, 12 + 16i, 40 - 42i];
```

Type:

```
z = convec(x, y)
```

```
z =
```

```
1.0e+02 *
```

```
Columns 1 through 4
```

```
0.1800 - 0.2600i    0.9600 + 0.2800i    1.3200 - 1.4400i  
3.7600 - 0.1200i
```

```
Column 5
```

```
1.5400 - 4.1400i
```

which agrees with the results the built-in MATLAB function `conv.m` produces.

## Dynamically Allocate Memory

To allocate memory dynamically in a Fortran MEX file, use `%val`. (See “Using the Fortran `%val` Construct” on page 6-6.) The example `dblmat.F` takes an input matrix of real data and doubles each of its elements. To see the source code, open the file in MATLAB Editor. `compute.F` is the subroutine `dblmat` calls to double the input matrix. (Open the file in MATLAB Editor.)

To build this example, at the command prompt type:

```
mex dblmat.F compute.F
```

For the 2-by-3 matrix, type:

```
x = [1 2 3; 4 5 6];  
y = dblmat(x)
```

```
y =  
    2     4     6  
    8    10    12
```

---

**Note:** The `dblmat.F` example, as well as `fulltosparse.F` and `sincall.F`, are split into two parts, the gateway and the computational subroutine, because of restrictions in some compilers.

---

## Handle Sparse Matrices

MATLAB provides a set of functions that allow you to create and manipulate sparse matrices. There are special parameters associated with sparse matrices, namely `ir`, `jc`, and `nzmax`. For information on how to use these parameters and how MATLAB stores sparse matrices in general, see “Sparse Matrices” on page 4-11.

---

**Note:** Sparse array indexing is zero-based, not one-based.

---

The `fulltosparse.F` example illustrates how to populate a sparse matrix. To see the source code, open the file in MATLAB Editor. `loadsparse.F` is the subroutine `fulltosparse` calls to fill the `mxArray` with the sparse data. (Open the file in MATLAB Editor.)

To build this example, at the command prompt type:

```
mex fulltosparse.F loadsparse.F
```

At the command prompt, type:

```
full = eye(5)

full =
     1     0     0     0     0
     0     1     0     0     0
     0     0     1     0     0
     0     0     0     1     0
     0     0     0     0     1
```

MATLAB creates a full, 5-by-5 identity matrix. Using `fulltosparse` on the full matrix produces the corresponding sparse matrix:

```
spar = fulltosparse(full)

spar =
    (1,1)     1
    (2,2)     1
    (3,3)     1
    (4,4)     1
    (5,5)     1
```



## Call MATLAB Functions from Fortran MEX Files

You can call MATLAB functions, operators, user-defined functions, and other binary MEX files from within your Fortran source code by using the API function `mexCallMATLAB`. The `sincall.F` example creates an `mxArray`, passes various pointers to a local function to acquire data, and calls `mexCallMATLAB` to calculate the sine function and plot the results. To see the source code, open the file in MATLAB Editor. `fill.F` is the subroutine `sincall` calls to fill the `mxArray` with data. (Open the file in MATLAB Editor.)

It is possible to use `mexCallMATLAB` (or any other API routine) from within your computational Fortran subroutine. You can only call most MATLAB functions with double-precision data. Some functions that perform computations, such as the `eig` function, do not work correctly with data that is not double precision.


To build this example, at the command prompt type:

```
mex sincall.F fill.F
```

Running this example:

```
sincall
```

displays the results:



---

**Note:** You can generate an object of type `mxUNKNOWN_CLASS` using `mexCallMATLAB`. See the following example.

---

This function returns two variables but only assigns one of them a value:

```
function [a,b]=foo[c]
a=2*c;
```

If you then call `foo` using `mexCallMATLAB`, the unassigned output variable is now of type `mxUNKNOWN_CLASS`.

## Debug Fortran Source MEX-Files

### In this section...

“Notes on Debugging” on page 6-31

“Debugging on Microsoft Windows Platforms” on page 6-31

“Debugging on Linux Platforms” on page 6-31

### Notes on Debugging

The examples show how to debug `timestwo.F`, found in your `matlabroot/extern/examples/refbook` folder.

Binary MEX files built with the `-g` option do not execute on other computers because they rely on files that are not distributed with MATLAB software. For more information on isolating problems with MEX files, see “Troubleshoot MEX Files”.

### Debugging on Microsoft Windows Platforms

For MEX files compiled with any version of the Intel® Visual Fortran compiler, you can use the debugging tools found in your version of Microsoft Visual Studio. Refer to the “Creating C/C++ Language MEX Files” topic “Debug on Microsoft Windows Platforms” on page 5-53 for instructions on using this debugger.

### Debugging on Linux Platforms

The MATLAB supported Fortran compiler `g95` has a `-g` option for building binary MEX files with debug information. Such files can be used with `gdb`, the GNU Debugger. This section describes using `gdb`.

#### GNU Debugger `gdb`

In this example, the MATLAB command prompt `>>` is shown in front of MATLAB commands, and `linux>` represents a Linux prompt; your system might show a different prompt. The debugger prompt is `<gdb>`.

1 To compile the source MEX file, type:

```
linux> mex -g timestwo.F
```

- 2 At the Linux prompt, start the gdb debugger using the `matlab -D` option:

```
linux> matlab -Dgdb
```

- 3 Start MATLAB without the Java Virtual Machine (JVM) by using the `-nojvm` startup flag:

```
<gdb> run -nojvm
```

- 4 In MATLAB, enable debugging with the `dbmex` function and run your binary MEX file:

```
>> dbmex on  
>> y = timestwo(4)
```

- 5 You are ready to start debugging.

It is often convenient to set a breakpoint at `mexFunction` so you stop at the beginning of the gateway routine.

---

**Note:** The compiler might alter the function name. For example, it might append an underscore. To determine how this symbol appears in a given MEX file, use the Linux command `nm`. For example:

```
linux> nm timestwo.mexa64 | grep -i mexfunction
```

The operating system responds with something like:

```
0000091c T mexfunction_
```

Use `mexFunction` in the breakpoint statement. Be sure to use the correct case.

---

```
<gdb> break mexfunction_  
<gdb> continue
```

- 6 Once you hit one of your breakpoints, you can make full use of any commands the debugger provides to examine variables, display memory, or inspect registers.

To proceed from a breakpoint, type `continue`:

```
<gdb> continue
```

- 7 After stopping at the last breakpoint, type:

```
<gdb> continue
```

timestwo finishes and MATLAB displays:

```
y =
```

```
      8
```

- 8 From the MATLAB prompt you can return control to the debugger by typing:

```
>> dbmex stop
```

Or, if you are finished running MATLAB, type:

```
>> quit
```

- 9 When you are finished with the debugger, type:

```
<gdb> quit
```

You return to the Linux prompt.

Refer to the documentation provided with your debugger for more information on its use.

## More About

- “Fortran Source Files”

## Handling Large mxArray

### In this section...

“Using the 64-Bit API” on page 6-34

“Building the Binary MEX File” on page 6-36

“Caution Using Negative Values” on page 6-36

“Building Cross-Platform Applications” on page 6-36

Binary MEX-files built on 64-bit platforms can handle 64-bit mxArray. These large data arrays can have up to  $2^{48}-1$  elements. The maximum number of elements a sparse mxArray can have is  $2^{48}-2$ .

Using the following instructions creates platform-independent binary MEX-files as well.

Your system configuration can affect the performance of MATLAB. The 64-bit processor requirement enables you to create the mxArray and access data in it. However, the system memory, in particular the size of RAM and virtual memory, determine the speed at which MATLAB processes the mxArray. The more memory available, the faster the processing.

The amount of RAM also limits the amount of data you can process at one time in MATLAB. For guidance on memory issues, see “Strategies for Efficient Use of Memory”. Memory management within source MEX-files can have special considerations, as described in “Memory Management” on page 5-66.

### Using the 64-Bit API

The signatures of the API functions shown in the following table use the `mwSize` or `mwIndex` types to work with a 64-bit mxArray. The variables you use in your source code to call these functions must be the correct type.

#### mxArray Functions Using `mwSize`/`mwIndex`

<code>mxCalcSingleSubscript</code>	<code>mxCreateSparseLogicalMatrix</code> <sup>2</sup>
<code>mxMalloc</code>	<code>mxCreateStructArray</code>
<code>mxCopyCharacterToPtr</code> <sup>1</sup>	<code>mxCreateStructMatrix</code>

<code>mxCopyComplex16ToPtr<sup>1</sup></code>	<code>mxGetCell</code>
<code>mxCopyComplex8ToPtr<sup>1</sup></code>	<code>mxGetDimensions</code>
<code>mxCopyInteger1ToPtr<sup>1</sup></code>	<code>mxGetElementSize</code>
<code>mxCopyInteger2ToPtr<sup>1</sup></code>	<code>mxGetField</code>
<code>mxCopyInteger4ToPtr<sup>1</sup></code>	<code>mxGetFieldByNumber</code>
<code>mxCopyPtrToCharacter<sup>1</sup></code>	<code>mxGetIr</code>
<code>mxCopyPtrToComplex16<sup>1</sup></code>	<code>mxGetJc</code>
<code>mxCopyPtrToComplex8<sup>1</sup></code>	<code>mxGetM</code>
<code>mxCopyPtrToInteger1<sup>1</sup></code>	<code>mxGetN</code>
<code>mxCopyPtrToInteger2<sup>1</sup></code>	<code>mxGetNumberOfDimensions</code>
<code>mxCopyPtrToInteger4<sup>1</sup></code>	<code>mxGetNumberOfElements</code>
<code>mxCopyPtrToPtrArray<sup>1</sup></code>	<code>mxGetNzmax</code>
<code>mxCopyPtrToReal14<sup>1</sup></code>	<code>mxGetProperty</code>
<code>mxCopyPtrToReal18<sup>1</sup></code>	<code>mxGetString</code>
<code>mxCopyReal14ToPtr<sup>1</sup></code>	<code>mxMalloc</code>
<code>mxCopyReal18ToPtr<sup>1</sup></code>	<code>mxRealloc</code>
<code>mxCreateCellArray</code>	<code>mxSetCell</code>
<code>mxCreateCellMatrix</code>	<code>mxSetDimensions</code>
<code>mxCreateCharArray</code>	<code>mxSetField</code>
<code>mxCreateCharMatrixFromStrings</code>	<code>mxSetFieldByNumber</code>
<code>mxCreateDoubleMatrix</code>	<code>mxSetIr</code>
<code>mxCreateLogicalArray<sup>2</sup></code>	<code>mxSetJc</code>
<code>mxCreateLogicalMatrix<sup>2</sup></code>	<code>mxSetM</code>
<code>mxCreateNumericArray</code>	<code>mxSetN</code>
<code>mxCreateNumericMatrix</code>	<code>mxSetNzmax</code>
<code>mxCreateSparse</code>	<code>mxSetProperty</code>

<sup>1</sup>Fortran function only.

<sup>2</sup>C function only.

Functions in this API use the `mwIndex`, `mwSize`, and `mwPointer` preprocessor macros.

## Building the Binary MEX File

Use the `mex` build script option `-largeArrayDims` with the 64-bit API.

## Caution Using Negative Values

When using the 64-bit API, `mwSize` and `mwIndex` are equivalent to `INTEGER*8` in Fortran. This type is unsigned, unlike `INTEGER*4`, which is the type used in the 32-bit API. Be careful not to pass any negative values to functions that take `mwSize` or `mwIndex` arguments. Do not cast negative `INTEGER*4` values to `mwSize` or `mwIndex`; the returned value cannot be predicted. Instead, change your code to avoid using negative values.

## Building Cross-Platform Applications

If you develop cross-platform applications (programs that can run on both 32-bit and 64-bit architectures), pay attention to the upper limit of values you use for `mwSize` and `mwIndex`. The 32-bit application reads these values and assigns them to variables declared as `INTEGER*4` in Fortran. Be careful to avoid assigning a large `mwSize` or `mwIndex` value to an `INTEGER*4` or other variable that might be too small.



## Memory Management

When a MEX file returns control to MATLAB, it returns the results of its computations in the output arguments—the `mxArrays` contained in the left-side arguments `plhs[ ]`. These arrays must have a temporary scope, so do not pass arrays created with the `mexMakeArrayPersistent` function in `plhs`. MATLAB destroys any `mxArray` created by the MEX file that is not in `plhs`. MATLAB also frees any memory that was allocated in the MEX file using the `mxMalloc`, `mxMalloc`, or `mxRealloc` functions.

Any misconstructed arrays left over at the end of a binary MEX file execution have the potential to cause memory errors.

MathWorks recommends that MEX-file functions destroy their own temporary arrays and free their own dynamically allocated memory. It is more efficient to perform this cleanup in the source MEX-file than to rely on the automatic mechanism. For more information on memory management techniques, see the sections “Memory Management” on page 5-66 in *Creating C/C++ Language MEX Files* and “Memory Management Issues” on page 4-65.

## MATLAB Supports Fortran 77

MATLAB supports MEX files written in Fortran 77. When troubleshooting MEX files written in other versions of Fortran, refer to the Fortran Language Reference Manual, <http://h21007.www2.hp.com/portal/download/files/unprot/Fortran/docs/lrm/dflrm.htm>. This manual describes features for different versions of Fortran.

For example, the length of the following statement is less than 72 characters.

```
mwPointer mxGetN, mxSetM, mxSetN, mxCreateStructMatrix, mxGetM
```

However, when MATLAB expands the preprocessor macro, `mwPointer`, the length of the statement exceeds the limit supported by Fortran 77.

# Calling MATLAB Engine from C/C++ and Fortran Programs

---

- “Introducing MATLAB Engine API for C/C++ and Fortran” on page 7-2
- “Callbacks in Applications” on page 7-4
- “Call MATLAB Functions from C/C++ Applications” on page 7-5
- “Call MATLAB Functions from Fortran Applications” on page 7-7
- “Attach to Existing MATLAB Sessions” on page 7-9
- “Build Windows Engine Application” on page 7-11
- “Run Windows Engine Application” on page 7-12
- “Set Run-Time Library Path on Windows Systems” on page 7-13
- “Register MATLAB as a COM Server” on page 7-15
- “Build Linux Engine Application” on page 7-16
- “Build Mac OS X Engine Application” on page 7-17
- “Run Linux Engine Application” on page 7-18
- “Run Mac Engine Application” on page 7-19
- “Set Run-Time Library Path on Linux Systems” on page 7-20
- “Set Run-Time Library Path on Mac Systems” on page 7-21
- “Build Engine Applications with IDE” on page 7-23
- “Can't Start MATLAB Engine” on page 7-26
- “Debug MATLAB Functions Used in Engine Applications” on page 7-27
- “Multithreaded Applications” on page 7-28
- “User Input Not Supported” on page 7-29
- “Getting Started” on page 7-30

# Introducing MATLAB Engine API for C/C++ and Fortran

The MATLAB C/C++ and Fortran engine library contains routines that allow you to call MATLAB from your own programs, using MATLAB as a computation engine. Using the MATLAB engine requires an installed version of MATLAB; you cannot run the MATLAB engine on a machine that only has the MATLAB Runtime.

Engine programs are standalone programs. These programs communicate with a separate MATLAB process via pipes, on UNIX systems, and through a Microsoft Component Object Model (COM) interface, on Microsoft Windows systems. MATLAB provides a library of functions that allows you to start and end the MATLAB process, send data to and from MATLAB, and send commands to be processed in MATLAB.

Some of the things you can do with the MATLAB engine are:

- Call a math routine, for example, to invert an array or to compute an FFT from your own program. When employed in this manner, MATLAB is a powerful and programmable mathematical subroutine library.
- Build an entire system for a specific task. For example, the front end (user interface) is programmed in C/C++ and the back end (analysis) is programmed in MATLAB.

The MATLAB engine operates by running in the background as a separate process from your own program. Some advantages are:

- On UNIX systems, the engine can run on your machine, or on any other UNIX machine on your network, including machines of a different architecture. This configuration allows you to implement a user interface on your workstation and perform the computations on a faster machine located elsewhere on your network. For more information, see the `engOpen` reference page.
- Instead of requiring your program to link to the entire MATLAB program (a substantial amount of code), it links to a smaller engine library.

The MATLAB engine cannot read MAT-files in a format based on HDF5. These MAT-files save data using the `-v7.3` option of the `save` function or are opened using the `w7.3` mode argument to the C or Fortran `matOpen` function.

---

**Note:** To run MATLAB engine on the UNIX platform, you must have the C shell `csh` installed at `/bin/csh`.

---

## **Communicating with MATLAB Software**

On UNIX systems, the engine library communicates with the engine using pipes, and, if needed, `rsh` for remote execution. On Microsoft Windows systems, the engine library communicates with the engine using a Component Object Model (COM) interface.

### **More About**

- “MATLAB COM Integration” on page 12-2
- “MATLAB Engine API for Python”

### Callbacks in Applications

If you have a user interface that executes many callbacks through the MATLAB engine, force these callbacks to be evaluated in the context of the base workspace. Use `evalin` to specify the base workspace for evaluating the callback expression. For example:

```
engEvalString(ep,"evalin('base', expression)")
```

Specifying the base workspace ensures MATLAB processes the callback correctly and returns results for that call.

This advice does not apply to computational applications that do not execute callbacks.

#### See Also

`engEvalString` | `evalin`

## Call MATLAB Functions from C/C++ Applications


The program `engdemo.c`, in the `matlabroot/extern/examples/eng_mat` folder, illustrates how to call the engine functions from a standalone C program. For the Microsoft Windows version of this program, see `engwindemo.c`.

To see `engdemo.c`, open this file in MATLAB Editor.

To see the Windows version `engwindemo.c`, open this file.

There is a C++ version of `engdemo` in the `matlabroot\extern\examples\eng_mat` folder. To see `engdemo.cpp`, open this file.

The first part of this program starts MATLAB and sends it data. MATLAB analyzes the data and plots the results.



The program continues with:

Press Return to continue

Pressing **Return** continues the program:

Done for Part I.

Enter a MATLAB command to evaluate. This command should create a variable X. This program will then determine what kind of variable you created.

For example: `X = 1:5`

Entering `X = 17.5` continues the program execution.

```
X = 17.5
```

```
X =
```

```
    17.5000
```

```
Retrieving X...
```

```
X is class double
```

```
Done!
```

Finally, the program frees memory, closes the MATLAB engine, and exits.

### Related Examples

- “Build Windows Engine Application” on page 7-11
- “Build Linux Engine Application” on page 7-16

### More About


- “Build Engine Applications with IDE” on page 7-23



## Call MATLAB Functions from Fortran Applications

The program `fengdemo.F`, in the `matlabroot/extern/examples/eng_mat` folder, illustrates how to call the engine functions from a standalone Fortran program. To see the code, open this file.

Executing this program starts MATLAB, sends it data, and plots the results.



The program continues with:

```
Type 0 <return> to Exit
Type 1 <return> to continue
```

Entering 1 at the prompt continues the program execution:

```
1
MATLAB computed the following distances:
time(s)  distance(m)
1.00     -4.90
2.00     -19.6
3.00     -44.1
4.00     -78.4
5.00     -123.
6.00     -176.
7.00     -240.
8.00     -314.
9.00     -397.
```

10.0      -490.

Finally, the program frees memory, closes the MATLAB engine, and exits.

## Attach to Existing MATLAB Sessions

This example shows how to attach an engine program to a MATLAB session that is already running.

On a Windows platform, start MATLAB with `-automation` in the command line. When you call `engOpen`, it connects to this existing session. You should only call `engOpen` once, because any `engOpen` calls now connect to this one MATLAB session.

The `-automation` option also causes the command window to be minimized. You must open it manually.

On the Mac and Linux platforms, you cannot make an engine program connect to an existing MATLAB session.

Shut down any MATLAB sessions.

From the **Start** button on the Windows menu bar, click **Run**.

In MATLAB, capture the value returned by the command:

```
path = fullfile(matlabroot, 'bin', computer('arch'))
```

In the **Run** dialog box **Open** field, type the following command, replacing `path` with the value from the previous step:

```
path\matlab.exe -automation
```

Click **OK**. This starts MATLAB.

In MATLAB, copy the `engwindemo.c` example to a writable folder.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'eng_mat', 'engwindemo.c'), '.', 'f')
```

Build the example.

```
mex -client engine engwindemo.c
```

Run the `engwindemo` program by typing at the MATLAB prompt:

```
!engwindemo
```

This does not start another MATLAB session, but rather uses the MATLAB session that is already open.

### **More About**

- “Launch MATLAB as Automation Server in Desktop Mode” on page 14-16
- “MATLAB COM Integration” on page 12-2

## Build Windows Engine Application

This example shows how to verify the build process on Windows platforms using the C example `engwindemo.c`.

Start MATLAB as a user with administrator privileges. Based on your User Account Control (UAC) settings, you might need to right-click the MATLAB icon and select **Run as administrator**. If that option is not available, contact your system administrator.

Register MATLAB as a COM server.

```
!matlab -regserver
```

MATLAB displays a second, minimized command window. Close that window.

Verify your current folder is writable and copy the example.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'eng_mat', 'engwindemo.c'), '.', 'f')
```

Build the application.

```
mex -v -client engine engwindemo.c
```

### See Also

`mex`

### Related Examples

- “Call MATLAB Functions from C/C++ Applications” on page 7-5
- “Run Windows Engine Application” on page 7-12

### More About

- “Register MATLAB as a COM Server” on page 7-15

### Run Windows Engine Application

This example shows how to run the C example, `engwindemo.c`, from the Windows system prompt. You need to know the value of `matlabroot` (the folder where MATLAB is installed) and the value returned by the MATLAB `computer('arch')` command (`arch`).

Set the run-time library path by modifying the system PATH variable.

```
set PATH=matlabroot\bin\arch;%PATH%
```

Make sure that you include the `;` path terminator character.

Run the example. The `engwindemo` application must be on your system path.

```
engwindemo
```

MATLAB Starts and displays the results.

Click **Ok** in the MATLAB whos window to close the application.

#### See Also

`computer` | `matlabroot`

#### Related Examples

- “Build Windows Engine Application” on page 7-11
- “Call MATLAB Functions from C/C++ Applications” on page 7-5

#### More About

- “Set Run-Time Library Path on Windows Systems” on page 7-13

## Set Run-Time Library Path on Windows Systems

### In this section...

“Change Path Each Time You Run the Application” on page 7-13

“Permanently Change Path” on page 7-13

“Troubleshooting” on page 7-14

At run time, tell the operating system where the API shared libraries reside by setting the `Path` environment variable. Set the value to the path returned by the following MATLAB command:

```
res = fullfile(matlabroot, 'bin', computer('arch'))
```

### Change Path Each Time You Run the Application

To set the run-time library path from the Windows command prompt, type the following command, where `res` is the value returned from the `fullfile` command. Set the path every time you open the Windows Command Processor.

```
set PATH=res;%PATH%
```

You must set the path each time that you open the Windows prompt.

### Permanently Change Path

To set the run-time library path permanently to `res`, modify the `Path` variable using the Control Panel. For the setting to take effect, close the command prompt window, then open a new command prompt window.

To remove the run-time library path, follow the same instructions, deleting the path name from the variable.

#### Windows 7

- Select **Computer** from the Start menu.
- Choose **System properties** from the context menu.
- Click **Advanced system settings > Advanced** tab.
- Click **Environment Variables**.

- Under **System variables**, select **Path** and click **Edit**.
- Modify **Path** by inserting `res;` at the beginning of the **Variable value:** text field.
- Click **Ok** to close the dialog boxes, then close the **Control Panel** dialog box.

### Troubleshooting

If you have multiple versions of MATLAB installed on your system, the version you use to build your engine applications must be the first listed in your system **Path** environment variable. Otherwise, MATLAB displays `Can't start MATLAB engine`.



## Register MATLAB as a COM Server

To run the engine application on a Windows operating system, you must register MATLAB as a COM server. Do this for every session, to ensure that the current version of MATLAB is the registered version. If you run older versions, the registered version could change. If there is a mismatch of version numbers, MATLAB displays Can ' t start MATLAB engine.

To register MATLAB manually as a server, start MATLAB as a user with administrator privilege. Then type:

```
!matlab -regserver
```

Close the MATLAB window that appears.

### Build Linux Engine Application

This example shows how to verify the build process on a Linux platform using the C example `engdemo.c`.

Open MATLAB.

Verify your current folder is writable and copy the example.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'eng_mat', 'engdemo.c'), '.', 'f')
```

Build the application.

```
mex -v -client engine engdemo.c
```

#### See Also

`mex`

#### Related Examples

- “Call MATLAB Functions from C/C++ Applications” on page 7-5
- “Run Linux Engine Application” on page 7-18

## Build Mac OS X Engine Application

This example shows how to verify the build process on a Mac OS X platform using the C example `engdemo.c`.

Open MATLAB.

Verify your current folder is writable and copy the example.

```
copyfile(fullfile(matlabroot, 'extern', 'examples', 'eng_mat', 'engdemo.c'), '.', 'f')
```

Build the application.

```
mex -v -client engine engdemo.c
```

### See Also

`mex`

### Related Examples

- “Call MATLAB Functions from C/C++ Applications” on page 7-5
- “Run Mac Engine Application” on page 7-19

### Run Linux Engine Application

This example shows how to run the C example `engdemo.c` from the Linux system prompt. You need to know the value of `matlabroot`, the folder where MATLAB is installed.

Set the run-time library path. This command replaces the value, if any, in `LD_LIBRARY_PATH`.

```
setenv LD_LIBRARY_PATH matlabroot/bin/glnxa64:matlabroot/sys/os/glnxa64
```

Set the path. Make sure that you include the `:` path terminator character.

```
setenv PATH matlabroot/bin:$PATH
```

Run the example. The `engdemo` application must be on your system path.

```
./engdemo
```

MATLAB starts and displays a figure.

Press Return to close the figure.

Create variable `X`, for example:

```
X = 'hello'
```

MATLAB displays the results and closes.

### Related Examples

- “Build Linux Engine Application” on page 7-16
- “Call MATLAB Functions from C/C++ Applications” on page 7-5

### More About

- “Set Run-Time Library Path on Linux Systems” on page 7-20

## Run Mac Engine Application

This example shows how to run the C example `engdemo.c` from the Mac Terminal Window. You need to know the value of *matlabroot*, the folder where MATLAB is installed.

Set the run-time library path. This command replaces the value, if any, in `DYLD_LIBRARY_PATH`.

```
setenv DYLD_LIBRARY_PATH matlabroot/bin/maci64:matlabroot/sys/os/maci64
```

Set the path. Make sure that you include the `:` path terminator character.

```
setenv PATH matlabroot/bin:$PATH
```

Run the example. The `engdemo` application must be on your system path.

```
./engdemo
```

MATLAB starts and displays a figure.

Press Return to close the figure.

Create variable `X`, for example:

```
X = 'hello'
```

MATLAB displays the results and closes.

### Related Examples

- “Build Mac OS X Engine Application” on page 7-17
- “Call MATLAB Functions from C/C++ Applications” on page 7-5

### More About

- “Set Run-Time Library Path on Mac Systems” on page 7-21

### Set Run-Time Library Path on Linux Systems

At run time, tell the operating system where the API shared libraries reside by setting the environment variable `LD_LIBRARY_PATH`. Set the value to `matlabroot/bin/glnxa64:matlabroot/sys/os/glnxa64`.

The command you use depends on your shell. The command replaces the existing `LD_LIBRARY_PATH` value. If `LD_LIBRARY_PATH` is already defined, prepend the new value to the existing value.

If you have multiple versions of MATLAB installed on your system, the version you use to build your engine applications must be the first listed in your system `Path` environment variable. Otherwise, MATLAB displays `Can't start MATLAB engine`.

Set the path every time you run MATLAB. Alternatively, place the commands in a MATLAB startup script.

#### C Shell

Set the library path using the following command format.

```
setenv LD_LIBRARY_PATH matlabroot/bin/glnxa64:matlabroot/sys/os/glnxa64
```

You can place these commands in a startup script, such as `~/ .cshrc`.

#### Bourne Shell

Set the library path using the following command format.

```
LD_LIBRARY_PATH=matlabroot/bin/glnxa64:matlabroot/sys/os/glnxa64:LD_LIBRARY_PATH  
export LD_LIBRARY_PATH
```

You can place these commands in a startup script such as `~/ .profile`.

#### See Also

`matlabroot`

## Set Run-Time Library Path on Mac Systems

At run time, tell the operating system where the API shared libraries reside by setting the environment variable `DYLD_LIBRARY_PATH`. Set the value to `matlabroot/bin/maci64:matlabroot/sys/os/maci64`.

The command you use depends on your shell. The command replaces the existing `DYLD_LIBRARY_PATH` value. If `DYLD_LIBRARY_PATH` is already defined, prepend the new value to the existing value.

If you have multiple versions of MATLAB installed on your system, the version you use to build your engine applications must be the first listed in your system `Path` environment variable. Otherwise, MATLAB displays `Can't start MATLAB engine`.

Set the path every time you run MATLAB. Alternatively, place the commands in a MATLAB startup script.

### C Shell

Set the library path using the following command format.

```
setenv DYLD_LIBRARY_PATH matlabroot/bin/maci64:matlabroot/sys/os/maci64
```

For example, for MATLAB R2015a on a Mac system:

```
setenv DYLD_LIBRARY_PATH /Applications/MATLAB_R2015a.app/bin/maci64:/Applications/MATLAB_R2015a.app/bin
```

You can place these commands in a startup script, such as `~/ .cshrc`.

### Bourne Shell

Set the library path using the following command format.

```
DYLD_LIBRARY_PATH=matlabroot/bin/maci64:matlabroot/sys/os/maci64:DYLD_LIBRARY_PATH
export DYLD_LIBRARY_PATH
```

For example, for MATLAB R2015a on a Mac system:

```
DYLD_LIBRARY_PATH=/Applications/MATLAB_R2015a.app/bin/maci64:/Applications/MATLAB_R2015a.app/bin
export DYLD_LIBRARY_PATH
```

You can place these commands in a startup script such as `~/ .profile`.

**See Also**  
matlabroot



## Build Engine Applications with IDE

### In this section...

“Configuring the IDE” on page 7-23

“Engine Include Files” on page 7-23

“Engine Libraries” on page 7-23

“Library Files Required by libeng” on page 7-24

### Configuring the IDE

If your integrated development environment (IDE) has a MATLAB-supported compiler, you can use the IDE to build engine applications. For an up-to-date list of supported compilers, see the Supported and Compatible Compilers website.

Engine applications require the Engine Library `libeng`, the Matrix Library `libmx`, and supporting include files. When you build using the `mex` command, MATLAB is configured to locate these files. When you build in your IDE, you must configure the IDE to locate them. Where these settings are depends on your IDE. Refer to your product documentation.

### Engine Include Files

Header files contain function declarations with prototypes for the routines you access in the API libraries. These files are in the `matlabroot\extern\include` folder and are the same for Windows, Mac, and Linux systems. Engine applications use:

- `engine.h` — function prototypes for engine routines.
- `matrix.h` — definition of the `mxArray` structure and function prototypes for matrix access routines.

In your IDE, set the pre-processor include path to the value returned by the following MATLAB command:

```
fullfile(matlabroot, 'extern', 'include')
```

### Engine Libraries

You need the `libeng` and `libmx` shared libraries. The name of the file is platform-specific, as shown in the following table.

### Library File Names by Operating System

Windows <sup>a</sup>	Linux	Mac
libeng.lib	libeng.so	libeng.dylib
libmx.lib	libmx.so	libmx.dylib

- a. These files are located in the folder  
`fullfile(matlabroot, 'extern', 'lib', computer('arch'), 'microsoft')`.

Add these library names to your IDE configuration. Set the library path to the value returned by the following MATLAB command:

```
fullfile(matlabroot, 'bin', computer('arch'))
```

Refer to your IDE product documentation for instructions.

### Library Files Required by libeng

The `libeng` library requires additional third-party library files. MATLAB uses these libraries to support Unicode character encoding and data compression in MAT-files.

These library files must reside in the same folder as the `libmx` library. You can determine what these libraries are using the platform-specific commands shown in the following table. Once you identify these files, update your IDE.

### Library Dependency Commands

Windows	Linux	Mac
See the following instructions for Dependency Walker	<code>ldd -d libeng.so</code>	<code>otool -L libeng.dylib</code>

On Windows systems, to find library dependencies, use the third-party product Dependency Walker. Dependency Walker is a free utility that scans Windows modules and builds a hierarchical tree diagram of all dependent modules. For each module found, it lists all the functions exported by that module, and which of those functions are called by other modules. Download the Dependency Walker utility from the website <http://www.dependencywalker.com/>. See <http://www.mathworks.com/matlabcentral/answers/92362-how-do-i-determine-which-libraries-my-mex-file-or-stand-alone-application-requires> for information on using the Dependency Walker.

Drag and drop the `libeng.dll` file into the Depends window. Identify the dependent libraries and add them to your IDE configuration.

### **Related Examples**

- “Build Windows Engine Application” on page 7-11
- “Build Linux Engine Application” on page 7-16

### **External Websites**

- How can I compile a MATLAB Engine application using Microsoft Visual Studio 9.0 or 10.0?
- How can I build an Engine application using the Xcode IDE on Mac?

### Can't Start MATLAB Engine

If you have multiple versions of MATLAB installed on your system, the version you use to build your engine applications must be the first listed in your system `Path` environment variable. Otherwise, MATLAB displays `Can't start MATLAB engine`.

On Windows operating systems, you also must register MATLAB as a COM server. If you have multiple versions of MATLAB, the version you are using must be the registered version.

#### Related Examples

- “Register MATLAB as a COM Server” on page 7-15

## Debug MATLAB Functions Used in Engine Applications

When creating MATLAB functions for use in engine applications, it is good practice to debug the functions in MATLAB before calling them through the engine library functions.

Although you cannot use the MATLAB Editor/Debugger from an engine application, you can use the MATLAB workspace to examine variables passed to MATLAB. For example, you have the following MATLAB function:

```
function y = myfcn(x)
y = x+2;
end
```

Your engine application calls `myfcn` with your variable `mycmxarray`, as shown in the following code:

```
engPutVariable(ep, "aVar", mycmxarray);
engEvalString(ep, "result = myfcn(aVar)");
mycmxarrayResult = engGetVariable(ep, "result");
```

If you do not get the expected result, you can examine two possibilities: if the input, `mycmxarray`, is incorrect, or if the MATLAB function is incorrect.

To examine the input to `myfcn`, first modify the function to save the MATLAB workspace to the file `debugmyfcn.mat`.

```
function y = myfcn(x)
save debugmyfcn.mat
y = x+2;
end
```

Execute your engine application, then start MATLAB and load `debugmyfcn.mat`.

```
load debugmyfcn.mat
whos x
```

Variable `x` contains the value from `mycmxarray`. If `x` is not what you expect, debug your engine code. If `x` is correct, debug the MATLAB function. To debug `myfcn`, open the function in the MATLAB Editor/Debugger, and then call the function from the MATLAB command line:

```
myfcn(x)
```

### **Multithreaded Applications**

MATLAB libraries are not thread-safe. If you create multithreaded applications, make sure that only one thread accesses the engine application.

## User Input Not Supported

A MATLAB engine application runs MATLAB as a computational server. MATLAB functions that interact with the user or disrupt program flow are not supported. Examples of such functions include debugging commands, `input`, `keyboard`, and `pause`.

### Getting Started

To build an engine application, you need:

- The ability to write C/C++ or Fortran source code. You can create these files with the MATLAB Editor.
- A compiler supported by MATLAB. For an up-to-date list of supported compilers, see the Supported and Compatible Compilers website.
- “C/C++ Matrix Library API” or “Fortran Matrix Library API” functions. However, the `mxGetProperty` and `mxSetProperty` functions are not supported for standalone applications.
- C and Fortran Engine Library functions.
- The `mex` build script with the `-client engine` option.
- To use your own build tools, see “Build Engine Applications with IDE” on page 7-23.

To run the application:

- “Set Run-Time Library Path on Windows Systems” on page 7-13
- “Register MATLAB as a COM Server” on page 7-15
- “Set Run-Time Library Path on Linux Systems” on page 7-20



# Engine API for Java

---

- “MATLAB Engine API for Java” on page 8-2
- “Build Java Engine Programs” on page 8-3
- “Java Example Source Code” on page 8-7
- “Java Engine API Summary” on page 8-8
- “Java Data Type Conversions” on page 8-11
- “Start and Close MATLAB Session from Java” on page 8-13
- “Connect Java to Running MATLAB Session” on page 8-16
- “Execute MATLAB Functions from Java” on page 8-19
- “Evaluate MATLAB Statements from Java” on page 8-22
- “Pass Variables from Java to MATLAB” on page 8-24
- “Pass Variables from MATLAB to Java” on page 8-26
- “Using Complex Variables in Java” on page 8-27
- “Using MATLAB Structures in Java” on page 8-29
- “Pass Java CellStr to MATLAB” on page 8-32
- “Using MATLAB Handle Objects in Java” on page 8-34
- “Redirect MATLAB Command Window Output to Java” on page 8-36
- “Run Simulink Simulation from Java” on page 8-38
- “MATLAB Engine API Exceptions” on page 8-42
- “Pass Java Array Arguments to MATLAB” on page 8-43
- “Incorrect Java Data Types” on page 8-45
- “Incorrect Number of Output Arguments” on page 8-47

## MATLAB Engine API for Java

The MATLAB Engine API for Java enables Java programs to interact with MATLAB synchronously or asynchronously, including:

- Start and terminate MATLAB.
- Connect to and disconnect from MATLAB sessions on the local machine.
- Call MATLAB functions with input arguments passed from Java and output variables returned from MATLAB.
- Evaluate MATLAB statements in the MATLAB base workspace.
- Pass variables from Java to MATLAB and MATLAB to Java.

Asynchronous communication with MATLAB is based on the Java Future interface, `java.util.concurrent.Future`.

The MATLAB Engine API for Java is included as part of the MATLAB product. You must have JDK™ 7 or a later version installed to build a MATLAB Engine application for Java.

### Related Examples

- “Java Engine API Summary” on page 8-8
- “Build Java Engine Programs” on page 8-3
- “Java Example Source Code” on page 8-7
- “Start and Close MATLAB Session from Java” on page 8-13

## Build Java Engine Programs

### In this section...

“General Requirements” on page 8-3

“Compile and Run Java Code on Windows” on page 8-3

“Compile and Run Java Code on Macintosh” on page 8-4

“Compile and Run Java Code on Linux” on page 8-5

### General Requirements

To set up your Java environment for building engine applications:

- Add `matlabroot/extern/engines/java/jar/engine.jar` to your Java class path.
- Build the engine application with JDK 7 or a later version.
- Ensure your JRE™ is not an earlier version than your JDK.

To run Java, add the folder `matlabroot/bin/<arch>` to your system environment variable. `<arch>` is your computer architecture. For example, `win64` for 64-bit Microsoft Windows machines, `maci64` on Macintosh, or `glnxa64` on Linux.

`matlabroot` is the value returned by the MATLAB `matlabroot` command. This command returns the folder where MATLAB is installed.

This table lists the names of the environment variables and the values of the paths.

Operating System	Variable	Path
Windows	PATH	<code>matlabroot\bin\win64</code>
64-bit Apple Mac	DYLD_LIBRARY_PATH	<code>matlabroot/bin/maci64</code>
64-bit Linux	LD_LIBRARY_PATH	<code>matlabroot/bin/ glnxa64:matlabroot/sys/os/ glnxa64</code>

### Compile and Run Java Code on Windows

Compile your Java code:

```
javac -classpath matlabroot\extern\engines\java\jar\engine.jar MyJavaCode.java
```

Run the Java program:

```
java -classpath .;matlabroot\extern\engines\java\jar\engine.jar MyJavaCode
```

### **Set System Path**

To set the runtime library path from the Windows command prompt, type the following command.

```
set PATH=matlabroot\bin\win64;%PATH%
```

Set the path every time you open the Windows Command Processor.

You can also set the PATH variable from the System Properties dialog box. **Control Panel > System > Advanced system settings > Advanced** tab. Click **Environment Variables**. Under **System variables**, select Path and click **Edit**. Modify Path by inserting *matlabroot*\bin\win64; at the beginning of the **Variable Value**. Click **OK** to close the dialog boxes, then close the **Control Panel** dialog box.

## **Compile and Run Java Code on Macintosh**

MATLAB engine API for Java supports only *maci64* on Macintosh systems.

Compile the Java code:

```
javac -classpath matlabroot/extern/engines/java/jar/engine.jar MyJavaCode.java
```

### **Specify Java Library Path and Run Program**

Specify the Java library path and run Java program in one statement.

```
java -Djava.library.path=matlabroot/bin/maci64 -classpath .:matlabroot/extern/engines/
```

### **Set System Variable and Run Program**

Set the DYLD\_LIBRARY\_PATH variable and run Java program. For example, using a C shell:

```
setenv DYLD_LIBRARY_PATH matlabroot/bin/maci64:$DYLD_LIBRARY_PATH  
java -classpath .:matlabroot/extern/engines/java/jar/engine.jar MyJavaCode
```

### Set Variables from C Shell

You can put these commands in a startup script, such as `~/ .cshrc`.

```
setenv DYLD_LIBRARY_PATH matlabroot/bin/maci64:$DYLD_LIBRARY_PATH
```

### Set Variables in Bourne Shell

You can put these commands in a startup script such as `~/ .profile`.

```
DYLD_LIBRARY_PATH=matlabroot/bin/maci64:$DYLD_LIBRARY_PATH
export DYLD_LIBRARY_PATH
```

## Compile and Run Java Code on Linux

MATLAB engine API for Java supports only `glnxa64` on Linux systems.

Compile Java code:

```
javac -classpath matlabroot/extern/engines/java/jar/engine.jar MyJavaCode.java
```

### Specify Java Library Path and Run Program

If a compatible GCC library is in the search path, you can add `matlabroot/bin/glnxa64` to the Java library search path and run the examples without setting the `DYLD_LIBRARY_PATH` variable. For information on supported compilers, see Supported and Compatible Compilers.

Specify the Java library path and run the Java program in one statement.

```
java -Djava.library.path=matlabroot/bin/glnxa64 -classpath matlabroot/extern/engines
```

### Set System Variable and Run Program

Set the `DYLD_LIBRARY_PATH` variable and run Java program. For example, using a C shell:

```
setenv LD_LIBRARY_PATH matlabroot/bin/glnxa64:matlabroot/sys/os/glnxa64:$LD_LIBRARY_PATH
java -classpath matlabroot/extern/engines/java/jar/engine.jar MyJavaCode
```

### Set Variables from C Shell

You can put these commands in a startup script, such as `~/ .cshrc`.

```
setenv LD_LIBRARY_PATH matlabroot/bin/glnxa64:matlabroot/sys/os/glnxa64:$LD_LIBRARY_PATH
```

### **Set Variables from Bourne Shell**

You can put these commands in a startup script such as `~/.profile`.

```
LD_LIBRARY_PATH=matlabroot/bin/glnxa64:matlabroot/sys/os/glnxa64:$LD_LIBRARY_PATH  
export LD_LIBRARY_PATH
```

### **Related Examples**

- “Java Engine API Summary” on page 8-8

## Java Example Source Code

The MATLAB engine API for Java ships with example code that you can use to test your environment and to become familiar with the use of the engine API. The Java source code is located in the *matlabroot*/extern/examples/engines/java folder, where *matlabroot* is the path returned by the MATLAB `matlabroot` command.

The folder contains these files:

- `EngineGUIDemo.java` — A Swing-based user interface that accepts an input number and uses MATLAB to calculate the factorial of the number.
- `EngineConsoleDemo.java` — A Java program that uses MATLAB logical indexing and mathematical functions to operate on a numeric matrix.
- `README` — A text file that describes how to build and run the examples.

To build these examples, first copy the files to a writable folder on your path. You can use the MATLAB `copyfile` function for this purpose:

```
copyfile(fullfile(matlabroot,'extern','examples','engines','java','EngineGUIDemo.java'),'')
copyfile(fullfile(matlabroot,'extern','examples','engines','java','EngineConsoleDemo.java'),'')
```

Follow the instructions in the `README` file to compile and run the examples.

### Related Examples

- “Build Java Engine Programs” on page 8-3

## Java Engine API Summary

In this section...
“com.mathworks Packages” on page 8-8
“com.mathworks.engine.MatlabEngine Methods” on page 8-8
“java.util.concurrent.Future Interface” on page 8-10

### com.mathworks Packages

Classes in com.mathworks Package	Purpose
com.mathworks.engine.MatlabEngine	Definition of the API for the Java engine
com.mathworks.engine.EnginExceptionio on page 8-42	Failure by MATLAB to start, connect, terminate, or disconnect
com.mathworks.engine.UnsupportedTy on page 8-42	Unsupported data type in input or output of MATLAB function
com.mathworks.engine.MatlabExecuti on page 8-42	Runtime error in MATLAB code
com.mathworks.engine.MatlabSyntaxE on page 8-42	Syntax error in MATLAB expression

The com.mathworks.matlab.types package provides support for specialized MATLAB types in Java.

Classes in com.mathworks.matlab.types Package	MATLAB Type
com.mathworks.matlab.types.Complex	MATLAB complex values in Java
com.mathworks.matlab.types.HandleObject	MATLAB handle objects in Java
com.mathworks.matlab.types.Struct	MATLAB struct (structures) in Java
com.mathworks.matlab.types.CellStr	Create a cell array of characters to pass to MATLAB

### com.mathworks.engine.MatlabEngine Methods

Static methods	Purpose
“startMatlab”	Start MATLAB synchronously



Static methods	Purpose
“startMatlabAsync”	Start MATLAB asynchronously
“findMatlab”	Find all available shared MATLAB sessions running on the local machine synchronously
“findMatlabAsync”	Find all available shared MATLAB sessions from local machine asynchronously
“connectMatlab”	Connect to a shared MATLAB session on local machine synchronously
“connectMatlabAsync”	Connect to a shared MATLAB session on local machine asynchronously

Member Methods	Purpose
“feval”	Evaluate a MATLAB function with arguments synchronously
“fevalAsync”	Evaluate a MATLAB function with arguments asynchronously
“eval”	Evaluate a MATLAB statement as a string synchronously
“evalAsync”	Evaluate a MATLAB statement as a string asynchronously
“getVariable”	Get a variable from the MATLAB base workspace synchronously
“getVariableAsync”	Get a variable from the MATLAB base workspace asynchronously
“putVariable”	Put a variable in the MATLAB base workspace synchronously
“putVariableAsync”	Put a variable in the MATLAB base workspace asynchronously
“disconnect”	Explicitly disconnect from the current MATLAB session synchronously
“disconnectAsync”	Explicitly disconnect from the current MATLAB session asynchronously

Member Methods	Purpose
“quit”	Force the shutdown of the current MATLAB session synchronously
“quitAsync”	Force the shutdown of the current MATLAB session asynchronously
“close”	Disconnect or terminate current MATLAB session

### **java.util.concurrent.Future Interface**

Member Methods	Purpose
get	Wait for the computation to complete and then return the result
cancel	Attempt to cancel execution of this task
isCancelled	Return <code>true</code> if this task was cancelled before it completed
isDone	Return <code>true</code> if this task completes

For more information, see the Java documentation for `java.util.concurrent.Future`.

## Java Data Type Conversions

### In this section...

“Pass Java Data to MATLAB” on page 8-11

“Pass MATLAB Data to Java” on page 8-11

### Pass Java Data to MATLAB

This table shows how the MATLAB engine API maps Java data types to MATLAB data types.

Java Type	MATLAB Type for Scalar Data	MATLAB Type for Array Data
boolean	logical	logical
bytes	int8	int8
short	int16	int16
int	int32	int32
long	int64	int64
float	single	single
double	double	double
char	char	char
java.lang.String	string	string
com.mathworks.matlab.types	struct	struct
com.mathworks.matlab.types	double	double
com.mathworks.matlab.types	MATLAB handle object	MATLAB handle object
com.mathworks.matlab.types	cellstr	cellstr
Nonrectangular (jagged) array	N/A	cell

### Pass MATLAB Data to Java

This table shows how the MATLAB engine API maps MATLAB data types to Java data types.

MATLAB Type	Java Type for Scalar Data	Java Type for Array Data
logical	Boolean	boolean[]
int8	Byte	byte[]
uint8	Byte	byte[]
int16	Short	short[]
uint16	Short	short[]
int32	Integer	int[]
uint32	Integer	int[]
int64	Long	long[]
uint64	Long	long[]
single	Long	long[]
double	Double	double[]
char	String	String
string	String	String[]
cellstr	String	String[]
Mixed cell array	N/A	Object[]
MATLAB handle object	com.mathworks.matlab.types	com.mathworks.matlab.types.HandleObjec
MATLAB value object	Unsupported	Unsupported
Complex number	com.mathworks.matlab.types	com.mathworks.matlab.types.Complex[]
struct	com.mathworks.matlab.types	com.mathworks.matlab.types.Struct[]

## More About

- “Java Engine API Summary” on page 8-8

## Start and Close MATLAB Session from Java

### In this section...

“Start MATLAB Synchronously” on page 8-13

“Start MATLAB Asynchronously” on page 8-13

“Start Engine with Startup Options” on page 8-14

“Close MATLAB Engine Session” on page 8-15

You can start a MATLAB session from your Java program synchronously or asynchronously. Use these `MatlabEngine` static methods to start MATLAB:

- `MatlabEngine.startMatlab` — Start a MATLAB session synchronously.
- `MatlabEngine.startMatlabAsync` — Start a MATLAB session asynchronously.

### Start MATLAB Synchronously

Start MATLAB from Java synchronously.

```
import com.mathworks.engine.*;

public class StartMatlab {
    public static void main(String[] args) throws Exception {
        MatlabEngine eng = MatlabEngine.startMatlab();
        ...
        eng.close();
    }
}
```

### Start MATLAB Asynchronously

Start MATLAB from Java asynchronously. Use the `get` method of the returned `Future` object to wait for the return of the `MatlabEngine` object.

```
import com.mathworks.engine.*;
import java.util.concurrent.Future;

public class StartMatlab {
    public static void main(String[] args) throws Exception {
        Future<MatlabEngine> engFuture = MatlabEngine.startMatlabAsync();
    }
}
```

```
        //Do work while MATLAB engine starts
        ...
        MatlabEngine eng = engFuture.get();
        ...
        eng.close();
    }
}
```

## Start Engine with Startup Options

You can specify MATLAB startup options when you start a MATLAB session. For information on MATLAB startup options, see “Commonly Used Startup Options”.

The `MatlabEngine.startMatlab` and `MatlabEngine.startMatlabAsync` methods accept a string array as an input.

Start the engine synchronously with MATLAB startup options.

```
import com.mathworks.engine.*;

public class StartMatlab {
    String[] options = {"-noFigureWindows", "-r", "cd H:"};
    public static void main(String[] args) throws Exception {
        MatlabEngine eng = MatlabEngine.startMatlab(options);
        ...
        eng.close();
    }
}
```

Start the engine asynchronously with MATLAB startup options.

```
import com.mathworks.engine.*;
import java.util.concurrent.Future;

public class StartMatlab {
    public static void main(String[] args) throws Exception {
        String[] options = {"-noFigureWindows", "-r", "cd H:"};
        Future<MatlabEngine> engFuture = MatlabEngine.startMatlabAsync(options);
        ...
        MatlabEngine eng = engFuture.get();
        ...
        eng.close();
    }
}
```

## Close MATLAB Engine Session

To end the MATLAB engine session, use one of these MatlabEngine methods:

Method	Purpose
"close"	<p>If a Java process starts the MATLAB session as a default non-shared session, <code>close()</code> terminates MATLAB.</p> <p>If the MATLAB session is a shared session, <code>close()</code> disconnects MATLAB from this Java process. MATLAB terminates when there are no other connections.</p>
"disconnect", "disconnectAsync"	Disconnect from the current MATLAB session synchronously or asynchronously.
"quit", "quitAsync"	Force the shutdown of the current MATLAB session synchronously or asynchronously.

### See Also

`com.mathworks.engine.MatlabEngine`

### More About

- "Connect Java to Running MATLAB Session" on page 8-16
- "Build Java Engine Programs" on page 8-3
- "Specify Startup Options"
- "Commonly Used Startup Options"

## Connect Java to Running MATLAB Session

### In this section...

“Find and Connect to MATLAB” on page 8-16

“Connect to MATLAB Synchronously” on page 8-16

“Connect to MATLAB Asynchronously” on page 8-17

“Specify Name of Shared Session” on page 8-17

### Find and Connect to MATLAB

You can connect the Java engine to shared MATLAB sessions that are running on the local machine. To connect to a shared MATLAB session:

- Start MATLAB as a shared engine session, or make a running MATLAB process shared using `matlab.engine.shareEngine`.
- Find the names of the MATLAB shared sessions using the `MatlabEngine.findMatlab` or `MatlabEngine.findMatlabAsync` static method.
- Pass the string containing the name of the shared MATLAB session to the `MatlabEngine.connectMatlab` or `MatlabEngine.connectMatlabAsync` static method. These methods connect the Java engine to the shared session.

If you do not specify the name of a shared MATLAB session when calling `MatlabEngine.connectMatlab` or `MatlabEngine.connectMatlabAsync`, the engine uses the first shared MATLAB session created. If there are no shared MATLAB sessions available, the engine creates a shared MATLAB session and connects to this session.

For a description of these methods, see `com.mathworks.engine.MatlabEngine`

### Connect to MATLAB Synchronously

Convert the MATLAB session to a shared session by calling `matlab.engine.shareEngine` from MATLAB.

```
matlab.engine.shareEngine
```

Find the session and connect synchronously from Java.

```
import com.mathworks.engine.*;
```



```

public class javaFindConnect {
    public static void main(String[] args) throws Exception {
        String[] engines = MatlabEngine.findMatlab();
        MatlabEngine eng = MatlabEngine.connectMatlab(engines[0]);
        // Execute command on shared MATLAB session
        eng.eval("plot(1:10); print('myPlot','-djpeg')");
        eng.close();
    }
}

```

## Connect to MATLAB Asynchronously

Convert the MATLAB session to a shared session by calling `matlab.engine.shareEngine` from MATLAB.

```
matlab.engine.shareEngine
```

Find the session and connect asynchronously from Java.

```

import com.mathworks.engine.*;
import java.util.concurrent.Future;

public class javaFindConnectAsync {
    public static void main(String[] args) throws Exception {
        Future<String[]> eFuture = MatlabEngine.findMatlabAsync();
        String[] engines = eFuture.get();
        Future<MatlabEngine> engFuture = MatlabEngine.connectMatlabAsync(engines[0]);
        // Work on other thread
        MatlabEngine eng = engFuture.get();
        // Execute command on shared MATLAB session
        Future<Void> vFuture = eng.evalAsync("plot(1:10); print('myPlot','-djpeg')");
        eng.close();
    }
}

```

## Specify Name of Shared Session

You can specify the name of the shared MATLAB session when you execute the `matlab.engine.shareEngine` MATLAB function. Doing so eliminates the need to use `MatlabEngine.findMatlab` or `MatlabEngine.findMatlabAsync` to find the name.

For example, start MATLAB and name the shared session `myMatlabEngine`.

```
matlab -r "matlab.engine.shareEngine('myMatlabEngine')"
```

Connect to the named MATLAB session from Java.

```
import com.mathworks.engine.*;

public class javaNameConnect {
    public static void main(String[] args) throws Exception {
        String[] myEngine = {"myMatlabEngine"};
        MatlabEngine eng = MatlabEngine.connectMatlab(myEngine[0]);
        // Execute command on shared MATLAB session
        eng.eval("plot(1:10); print('myPlot', '-djpeg')");
        eng.close();
    }
}
```

## Related Examples

- “Start and Close MATLAB Session from Java” on page 8-13

## Execute MATLAB Functions from Java

### In this section...

“Calling MATLAB Functions” on page 8-19

“Execute Function with Single Returned Argument” on page 8-19

“Execute Function with Multiple Returned Arguments” on page 8-20

“When to Specify Number of Output Arguments” on page 8-20

### Calling MATLAB Functions

You can execute MATLAB functions from Java using the `MatlabEngine feval` and `fevalAsync` methods. These methods work like the MATLAB `feval` function. Use `feval` and `fevalAsync` when you want to return the result of the function execution to Java or to pass arguments from Java.

To call a MATLAB function:

- Pass the function name as a string.
- Define the input arguments required by the MATLAB function.
- Specify the number of outputs expect from the MATLAB function (1 is assumed if not specified).
- Define the appropriate returned type for the outputs of the MATLAB function.
- Use writers to redirect output from the MATLAB command window to Java.

You can also use the `MatlabEngine eval` and `evalAsync` methods to evaluate MATLAB expressions. These methods enable you to create variables in the MATLAB workspace, but do not return values.

### Execute Function with Single Returned Argument

This example code uses the MATLAB `sqrt` function to find the square root of the elements in an array of doubles. The `feval` method returns a double array containing the results of the `sqrt` function call.

```
import com.mathworks.engine.*;

public class javaFevalFunc{
```

```
public static void main(String[] args) throws Exception{
    MatlabEngine eng = MatlabEngine.startMatlab();
    double[] a = {2.0 ,4.0, 6.0};
    double[] roots = eng.feval("sqrt", a);
    for (double e: roots) {
        System.out.println(e);
    }
    eng.close();
}
```

## Execute Function with Multiple Returned Arguments

This example code uses the MATLAB `gcd` function to find the greatest common divisor and Bézout coefficients from the two integer values passes as input arguments. The `feval` method returns an object array containing the results of the `gcd` function call. The returned values are integers.

Because the MATLAB `gcd` function is returning three output arguments, specify the number of returned values as the first argument to the `feval` method.

```
import com.mathworks.engine.*;

public class javaFevalFcnMulti {
    public static void main(String[] args) throws Exception {
        MatlabEngine eng = MatlabEngine.startMatlab();
        Object[] results = eng.feval(3, "gcd", 40, 60);
        Integer G = (Integer)results[0];
        Integer U = (Integer)results[1];
        Integer V = (Integer)results[2];
        eng.close();
    }
}
```

## When to Specify Number of Output Arguments

The MatlabEngine `feval` and `fevalAsync` methods enable you to specify the number of output arguments returned by the MATLAB function. By default, the number of output arguments from the MATLAB function is assumed to be 1.

If you want to call a MATLAB function with no outputs or more than one output, specify that number as the first argument passed to `feval` or `fevalAsync`.

For example, this code calls the MATLAB `gcd` function with the three output syntax:

```
Object[] results = eng.feval(3, "gcd", 40, 60);
```

MATLAB functions can behave differently depending on the number of outputs requested. Some functions can return no outputs or a specified number of outputs. For example, the MATLAB `pause` function holds execution for a specified number of seconds. However, if you call `pause` with an output argument, it returns immediately with a status value. Therefore, this code does not cause MATLAB to pause because `feval` requests one output argument.

```
eng.feval("pause", 10);
```

To pause MATLAB execution for the 10 seconds requested, specify the number of outputs as 0.

```
eng.feval(0, "pause", 10);
```

---

**Note:** To ensure that a MATLAB function is called with no outputs, specify the number of returned arguments as 0.

---

## Related Examples

- “Evaluate MATLAB Statements from Java” on page 8-22

## Evaluate MATLAB Statements from Java

**In this section...**

“Evaluating MATLAB Statements” on page 8-22

“Evaluate Mathematical Function in MATLAB” on page 8-22

### Evaluating MATLAB Statements

You can evaluate MATLAB statements from Java using the `MatlabEngine` `eval` and `evalAsync` methods. These methods are similar to the MATLAB `eval` function. However, the `eval` and `evalAsync` methods do not return the results of evaluating the MATLAB statement.

You can also use the `MatlabEngine` `feval` and `fevalAsync` methods to call MATLAB functions. These methods enable you to pass variables to the MATLAB workspace and return values to Java.

The input arguments named in the string must exist in the MATLAB workspace. You can assign the results of the evaluation to variables within the statement string. The variable names that you assign in the statement are created in the MATLAB base workspace. MATLAB does not require you to initialize the variables created in the expression.

To return the variables created in the MATLAB workspace, use the `MatlabEngine` `getVariable` or `getVariableAsync` methods.

### Evaluate Mathematical Function in MATLAB

This example code evaluates a mathematical function over a specified domain using two MATLAB statements. The `meshgrid` function creates MATLAB variables `X`, `Y`, and `Z` in the MATLAB workspace. These variables are used by the mathematical expression in the next call to `evalAsync`.

The `MatlabEngine` `getVariable` method returns the result of the evaluation to Java.

```
import com.mathworks.engine.*;

public class javaEvalFunc {
    public static void main(String[] args) throws Exception {
```

```
MatlabEngine eng = MatlabEngine.startMatlab();
eng.evalAsync("[X, Y] = meshgrid(-2:0.2:2);");
eng.evalAsync("Z = X .* exp(-X.^2 - Y.^2);");
Object[] Z = eng.getVariable("Z");
eng.close();
}
```

## Related Examples

- “Execute MATLAB Functions from Java” on page 8-19

## Pass Variables from Java to MATLAB

### In this section...

“Ways to Pass Variables” on page 8-24

“Pass Function Arguments” on page 8-24

“Put Variables in the MATLAB Workspace” on page 8-25

### Ways to Pass Variables

You can pass Java variables to MATLAB using these methods:

- Pass the variables as function arguments in calls to the `MatlabEngine feval` and `fevalAsync` methods. Variables passed as arguments to function calls are not stored in the MATLAB base workspace.
- Put the variables in the MATLAB base workspace using the `MatlabEngine putVariable` and `putVariableAsync` methods.

For information on type conversions, see “Java Data Type Conversions” on page 8-11.

### Pass Function Arguments

This example code passes the coefficients of a polynomial,  $x^2 - x - 6$ , to the MATLAB `roots` function.

- Define a double array `p` to pass as an argument for the MATLAB `roots` function.
- Define a double array `r` to accept the returned values.

```
import com.mathworks.engine.*;

public class javaPassArg{
    public static void main(String[] args) throws Exception{
        MatlabEngine eng = MatlabEngine.startMatlab();
        double[] p = {1.0, -1.0, -6.0};
        double[] r = eng.feval("roots", p);
        for (double e: r) {
            System.out.println(e);
        }
        eng.close();
    }
}
```



```
    }  
}
```

## Put Variables in the MATLAB Workspace

This example code puts variables in the MATLAB workspace and uses those variables as arguments in a MATLAB call to the MATLAB `complex` function. The MATLAB `who` command lists the workspace variables.

```
import com.mathworks.engine.*;  
import java.util.Arrays;  
  
public class javaPutVar {  
    public static void main(String[] args) throws Exception {  
        MatlabEngine eng = MatlabEngine.startMatlab();  
        eng.putVariable("x", 7.0);  
        eng.putVariable("y", 3.0);  
        eng.eval("z = complex(x, y);");  
        String[] w = eng.feval("who");  
        System.out.println("MATLAB workspace variables " + Arrays.toString(w));  
        eng.close();  
    }  
}
```

## Related Examples

- “Pass Variables from MATLAB to Java” on page 8-26
- “Base and Function Workspaces”

## Pass Variables from MATLAB to Java

Use the `MatlabEngine` `getVariable` or `getVariableAsync` methods to get variables from the MATLAB base workspace. To determine the appropriate mapping of MATLAB type to Java type, see “Java Data Type Conversions” on page 8-11.

### Coordinate Conversion

This example code uses the MATLAB `cart2sph` function to convert from Cartesian to spherical coordinates. The `getVariable` method gets the returned spherical coordinate variables from the MATLAB base workspace.

```
import com.mathworks.engine.*;

public class GetPolar {
    public static void main(String[] args) throws Exception {
        MatlabEngine eng = MatlabEngine.startMatlab();
        eng.eval("[az,e1,r] = cart2sph(5, 7, 3);");
        double az = eng.getVariable("az");
        double e1 = eng.getVariable("e1");
        double r = eng.getVariable("r");
        System.out.println("Azimuth: " + az);
        System.out.println("Elevation: " + e1);
        System.out.println("Radius " + r);
        eng.close();
    }
}
```

### Related Examples

- “Pass Variables from Java to MATLAB” on page 8-24
- “Java Data Type Conversions” on page 8-11

## Using Complex Variables in Java

### In this section...

“Complex Variables in MATLAB” on page 8-27

“Get Complex Variables from MATLAB” on page 8-27

“Pass Complex Variable to MATLAB Function” on page 8-28

### Complex Variables in MATLAB

MATLAB numeric types can represent complex numbers. The MATLAB Engine API supports complex variables in Java using the `com.mathworks.matlab.types.Complex` class. Using this class, you can:

- Create complex variables in Java and pass these variables to MATLAB.
- Get complex variables from the MATLAB base workspace.

MATLAB always uses double precision values for the real and imaginary parts of complex numbers.

### Get Complex Variables from MATLAB

This example code uses MATLAB functions to:

- Find the roots of a polynomial (`roots`)
- Find the complex conjugate of the complex roots (`conj`)
- Find the real result of multiplying the complex number array by its conjugate.

Use the `getVariable` method to return the complex variables to Java.

```
import com.mathworks.engine.*;
import com.mathworks.matlab.types.Complex;

public class javaGetVar {
    public static void main(String[] args) throws Exception {
        MatlabEngine eng = MatlabEngine.startMatlab();
        eng.eval("z = roots([1.0, -1.0, 6.0]);");
        eng.eval("zc = conj(z);");
        eng.eval("rat = z.*zc;");
    }
}
```

```
Complex[] z = eng.getVariable("z");
Complex[] zc = eng.getVariable("zc");
double[] rat = eng.getVariable("rat");
for (Complex e: z) {
    System.out.println(e);
}
for (Complex e: zc) {
    System.out.println(e);
}
for (double e: rat) {
    System.out.println(e);
}
eng.close();
}
}
```

## Pass Complex Variable to MATLAB Function

This example code creates a `com.mathworks.matlab.types.Complex` variable in Java and passes it to the MATLAB `real` function. This function returns the real part of the complex number. The value returned by MATLAB is of type `double` even though the original variable created in Java is an `int`.

```
import com.mathworks.engine.*;
import com.mathworks.matlab.types.Complex;

public class javaComplexVar {
    public static void main(String[] args) throws Exception {
        MatlabEngine eng = MatlabEngine.startMatlab();
        int r = 8;
        int i = 3;
        Complex c = new Complex(r, i);
        double real = eng.feval("real", c);
        eng.close();
    }
}
```

## Related Examples

- “Java Data Type Conversions” on page 8-11

## Using MATLAB Structures in Java

### In this section...

“MATLAB Structures” on page 8-29

“Pass Struct to MATLAB Function” on page 8-29

“Get Struct from MATLAB” on page 8-30

### MATLAB Structures

MATLAB structures contain data and references it using field names. Each field can contain any type of data. MATLAB code accesses data in a structure using dot notation of the form `structName.fieldName`. The class of a MATLAB structure is `struct`.

The Java `com.mathworks.matlab.types.Struct` class enables you to:

- Create a `Struct` in Java and pass it to MATLAB.
- Create a MATLAB `struct` and return it to Java.

The `com.mathworks.matlab.types.Struct` class implements the `java.util.Map` interface. However, you cannot change the mappings, keys, or values of a `Struct` returned from MATLAB.

### Pass Struct to MATLAB Function

The MATLAB `set` function sets the properties of MATLAB graphics objects. To set several properties in one call to `set`, it is convenient to use a MATLAB `struct`. Define this `struct` with field names that match the names of the properties that you want to set. The value referenced by the field is the value assigned the property.

This example code performs the following steps:

- Start MATLAB.
- Pass a double array to the MATLAB `plot` function.
- Return the MATLAB handle object to Java as a `com.mathworks.matlab.types.HandleObject`.
- Create a `com.mathworks.matlab.types.Struct` using property names and values.

- Create a MATLAB graph and display it for 5 seconds.
- Pass the `HandleObject` and the `Struct` to the MATLAB `set` function using `feval`. This function changes the color and line width of the plotted data.
- Export the plot to the `jpeg` file named `myPlot` and closes the engine connection.

```
import com.mathworks.engine.*;
import com.mathworks.matlab.types.*;

public class CreateStruct {
    public static void main(String[] args) throws Exception {
        MatlabEngine eng = MatlabEngine.startMatlab();
        double[] y = {1.0, 2.0, 3.0, 4.0, 5.0};
        HandleObject h = eng.feval("plot", y);
        eng.eval("pause(5)");
        double[] color = {1.0, 0.5, 0.7};
        Struct s = new Struct("Color", color, "LineWidth", 2);
        eng.feval("set", h, s);
        eng.eval("print('myPlot', '-djpeg')");
        eng.close();
    }
}
```

## Get Struct from MATLAB

The MATLAB `axes` function creates axes for a graph and returns a handle object reference. The MATLAB `get` function, when called with one output, returns a MATLAB `struct` with the properties of the graphics object.

This example code:

- Creates a MATLAB graphics object and returns the object handle as a `HandleObject`.
- Creates a MATLAB structure containing the properties and values of the graphics object and returns it as a `Struct`.
- Gets the value of the `FontName` property from the `Struct`.
- Attempts to change the value of the `FontName` key, which throws an `UnsupportedOperationException` because the `Struct` is unmodifiable.

```
import com.mathworks.engine.*;
import com.mathworks.matlab.types.*;
```

```
public class GetStruct {
    public static void main(String[] args) throws Exception {
        MatlabEngine eng = MatlabEngine.startMatlab();
        HandleObject h = eng.feval("axes");
        Struct s = eng.feval("get", h);
        Object fontName = s.get("FontName");
        System.out.println("The font name is " + fontName.toString());
        try {
            s.put("FontName", "Times");
        } catch (UnsupportedOperationException e) {
            e.printStackTrace();
        }
        eng.close();
    }
}
```

## Related Examples

- “Java Data Type Conversions” on page 8-11

## Pass Java CellStr to MATLAB

### In this section...

“MATLAB Cell Arrays” on page 8-32

“Create CellStr” on page 8-32

### MATLAB Cell Arrays

MATLAB cell arrays can contain variable-length character vectors in each cell. Some MATLAB functions require cell arrays of character vectors as input arguments. Use the `com.mathworks.matlab.types.CellStr` class to define a cell array of character vectors in Java.

The MATLAB engine converts MATLAB cell arrays of character vectors to Java `String` arrays when passed from MATLAB to Java.

### Create CellStr

This example code creates a `MATLAB containers.Map` instance by passing a `CellStr` object and a double array as arguments to the `MATLAB containers.Map` constructor.

Because `containers.Map` is a MATLAB handle class, define the returned type as a `com.mathworks.matlab.types.HandleObject`.

The `containers.Map keys` method returns a MATLAB `cellstr` with the key names. However, the `MatlabEngine feval` method returns a `String` array to Java.

```
import com.mathworks.engine.*;
import com.mathworks.matlab.types.*;

public class CellArrays {
    public static void main(String[] args) throws Exception {
        MatlabEngine eng = MatlabEngine.startMatlab();
        CellStr keyCellStr = new CellStr(new String[]{"One", "Two", "Three"});
        double[] valueObject = {1.0, 2.0, 3.0};
        HandleObject myMap = eng.feval("containers.Map", keyCellStr, valueObject);
        String[] keysArray = eng.feval("keys", myMap);
        for (String e: keysArray) {
            System.out.println(e);
        }
    }
}
```



```
        eng.close();  
    }  
}
```

## **Related Examples**

- “Java Data Type Conversions” on page 8-11

## Using MATLAB Handle Objects in Java

### In this section...

“MATLAB Handle Objects” on page 8-34

“Java HandleObject Class” on page 8-34

“Set Graphics Object Properties from Java” on page 8-34

### MATLAB Handle Objects

MATLAB handle objects are instances of the handle class. Accessing MATLAB handle objects enables you to set the values of public properties on those objects. For example, all MATLAB graphics and user interface objects are handle objects.

### Java HandleObject Class

Use the `com.mathworks.matlab.types.HandleObject` class to represent handle objects returned from MATLAB to Java. You can pass the `HandleObject` instance only to the MATLAB session in which it was created. You cannot construct a `HandleObject` in Java.

### Set Graphics Object Properties from Java

The MATLAB `plot` function returns the handle objects referencing the lines in the graph. Use these handles with the `set` function to modify the appearance of the graph by changing the properties of the lines.

This example executes the following function calls in MATLAB:

```
% Create a 2-by-3 array of doubles
data = [1,2,3;-1,-2,-3];
% Plot the data and return the line handles
h = plot(data);
% Set the line width to 2 points
set(h,'LineWidth',2);
% Pause for 5 seconds, just to see the result
pause(5)
```

The Java code uses these steps to cause the execution of the MATLAB code as described:

- Create a 2D double array called `data`.
- Cast the `data` array to an `Object` so MATLAB interprets the array as one argument to `plot`.
- Return `HandleObject` array `h` from MATLAB with the line handles.
- Call the MATLAB `set` function to set the `LineWidth` property of the line handles to 2.0. Convert the name of the `LineWidth` property from a `String` to a `char[]` because the `set` function requires property names to be MATLAB char arrays.
- Pause for 5 seconds and then close the MATLAB engine.

```
import com.mathworks.engine.*;
import com.mathworks.matlab.types.*;

public class PassHandleObject {
    public static void main(String[] args) throws Exception {
        MatlabEngine eng = MatlabEngine.startMatlab();
        double[][] data = {{1.0, 2.0, 3.0}, {-1.0, -2.0, -3.0}};
        HandleObject[] h = eng.feval("plot", (Object) data);
        String lw = ("LineWidth");
        eng.feval(0, "set", h, lw.toCharArray(), 2.0);
        eng.eval("pause(5)");
        eng.close();
    }
}
```

## Related Examples

- “Java Data Type Conversions” on page 8-11

## Redirect MATLAB Command Window Output to Java

### In this section...

“Output to MATLAB Command Window” on page 8-36

“Redirect MATLAB Output” on page 8-36

“Redirect MATLAB Error Messages to Java” on page 8-37

### Output to MATLAB Command Window

MATLAB displays error messages and the output from functions that are not terminated with a semicolon in the MATLAB command window. You can redirect this output to Java using a `java.io.StringWriter`. The MatlabEngine `feval`, `fevalAsync`, `eval`, and `evalAsync` methods support the use of output streams to redirect MATLAB output.

### Redirect MATLAB Output

The MATLAB `whos` command displays information about the current workspace variables in the MATLAB command window. Use a `StringWriter` to stream this output to Java.

```
import com.mathworks.engine.*;
import java.io.*;

public class RedirectOutput {
    public static void main(String[] args) throws Exception {
        MatlabEngine engine = MatlabEngine.startMatlab();
        // Evaluate expressions that create variables
        eng.evalAsync("[X,Y] = meshgrid(-2:.2:2);");
        eng.evalAsync("Z = X.*exp(-X.^2 - Y.^2);");
        // Get the output of the whos command
        StringWriter writer = new StringWriter();
        eng.eval("whos", writer, null);
        System.out.println(writer.toString());
        writer.close();
        eng.close();
    }
}
```

## Redirect MATLAB Error Messages to Java

This example code attempts to evaluate a MATLAB statement that has a syntax error (unbalanced single quotation marks). Entering this statement in MATLAB causes an error:

```
disp('Hello')
```

MATLAB returns this error message in the command window:

```
disp('Hello')
      ^
Error: Character vector is not terminated properly.
```

To redirect this error message to Java, use a `StringWriter` with the `eval` method. Catch the `MatlabSyntaxException` exception thrown by the error and write the MATLAB error message to Java.

```
import com.mathworks.engine.*;
import java.io.*;

public class javaRedirectOut {
    public static void main(String[] args) throws Exception {
        MatlabEngine engine = MatlabEngine.startMatlab();
        StringWriter writer = new StringWriter();
        try {
            eng.eval("disp('Hello')", null, writer);
        } catch (MatlabSyntaxException e) {
            System.out.println("Error redirected to Java: ");
            System.out.println(writer.toString());
        }
        writer.close();
        eng.close();
    }
}
```

## Related Examples

- “Evaluate MATLAB Statements from Java” on page 8-22

## Run Simulink Simulation from Java

<b>In this section...</b>
“MATLAB Command to Run Simulation” on page 8-38
“Run vdp Model from Java” on page 8-38

### MATLAB Command to Run Simulation


You can run Simulink simulations using the MATLAB Engine API for Java. Here are the basic steps to run a simulation programmatically.

- Create a MATLAB engine object and start a MATLAB session.
- Load the Simulink model in MATLAB (`load_system`).
- Run the simulation with specific simulation parameters (`sim`).
- Access the results of the simulation using methods of the returned `Simulink.SimulationOutput` object.

For information on running simulations programmatically from MATLAB, see “Programmatic Simulation”.

### Run vdp Model from Java

The Simulink `vdp` block diagram simulates the van der Pol equation, which is a second order differential equation. The model solves the equations using the initial conditions and configuration parameters defined by the model.



### MATLAB Code to Run Simulation

This MATLAB code shows the commands to run the simulation programmatically. The `Simulink.SimulationOutput` object `get` method returns the results and time vector.

```
mdl = 'vdp';
load_system(mdl);
simOut = sim(mdl, 'SaveOutput', 'on', ...
    'OutputSaveName', 'yOut', ...
    'SaveTime', 'on', ...
    'TimeSaveName', 'tOut');
y = simOut.get('yOut');
t = simOut.get('tOut');
```

### Graph the Data

This MATLAB code creates a graph of the simulation output and exports the graph to a JPEG image file.

```
plot(t,y)
print('vdpPlot', '-djpeg')
```

### Java Code to Run Simulation

This Java code runs the Simulink `vdp` model simulation and returns the results to Java. The implementation performs these operations:

- Creates a MATLAB engine object and start a MATLAB session.
- Calls the MATLAB `load_system` command to start Simulink and load the `vdp` model asynchronously. Poll the task until the `Future` returns.
- Calls the MATLAB `sim` command to set simulation parameters and run the simulation. Poll the task until the `Future` returns.
- Captures the result of the simulation. The output of the `sim` function is a MATLAB `Simulink.SimulationOutput` object, which is created in the MATLAB base workspace.

The engine API does not support this type of object. Therefore, this example uses the object `get` method to access the simulation data in the MATLAB workspace.

- Creates a graphic of the simulation data and exports this graph to a JPEG file.
- Returns the simulation results and time vector to Java as `double` arrays.

```
import com.mathworks.engine.*;
import java.util.concurrent.Future;
import java.util.Arrays;

public class RunSimulation {
    public static void main(String[] args) throws Exception {
        MatlabEngine eng = MatlabEngine.startMatlab();
        Future<Void> fLoad = eng.evalAsync("load_system('vdp')");
        while (!fLoad.isDone()){
            System.out.println("Loading Simulink model...");
            Thread.sleep(10000);
        }
        Future<Void> fSim = eng.evalAsync("simOut = sim('vdp','SaveOutput'," +
            "'on','OutputSaveName','yOut'," +
            "'SaveTime','on','TimeSaveName','tOut');");
        while (!fSim.isDone()) {
            System.out.println("Running Simulation...");
            Thread.sleep(10000);
        }
        // Get simulation data
        eng.eval("y = simOut.get('yOut');");
        eng.eval("t = simOut.get('tOut');");
        // Graph results and create image file
        eng.eval("plot(t,y)");
    }
}
```



```
eng.eval("print('vdpPlot','-djpeg')");  
// Return results to Java  
double[][] y = eng.getVariable("y");  
double[] t = eng.getVariable("t");  
// Display results  
System.out.println("Simulation result " + Arrays.deepToString(y));  
System.out.println("Time vector " + Arrays.toString(t));  
eng.close();  
    }  
}
```

## Related Examples

- “Evaluate MATLAB Statements from Java” on page 8-22
- “Pass Variables from Java to MATLAB” on page 8-24
- “Pass Variables from MATLAB to Java” on page 8-26

## MATLAB Engine API Exceptions

In this section...
“com.mathworks.engine.EngineException” on page 8-42
“com.mathworks.engine.UnsupportedTypeException” on page 8-42
“com.mathworks.engine.MatlabExecutionException” on page 8-42
“com.mathworks.engine.MatlabSyntaxException” on page 8-42

### **com.mathworks.engine.EngineException**

The `com.mathworks.engine.EngineException` occurs if MATLAB fails to start, fails to connect, terminates, or disconnects. Use the `getMessage` method to get a detailed message string returned by this exception.

### **com.mathworks.engine.UnsupportedTypeException**

The `com.mathworks.engine.UnsupportedTypeException` occurs if you use an unsupported data type in either the input or output of a MATLAB function. Use the `getMessage` method to get a detailed message string returned by this exception.

### **com.mathworks.engine.MatlabExecutionException**

The `com.mathworks.engine.MatlabExecutionException` occurs if there is a runtime error in a MATLAB command. This class inherits from `java.util.ExecutionException`.

### **com.mathworks.engine.MatlabSyntaxException**

The `com.mathworks.engine.MatlabSyntaxException` occurs if there is a syntax error in a MATLAB command. This class inherits from `java.util.ExecutionException`.

### **Related Examples**

- “Java Engine API Summary” on page 8-8

## Pass Java Array Arguments to MATLAB

### In this section...

“2-D Array Arguments for MATLAB Functions” on page 8-43

“Multidimensional Arrays” on page 8-43

### 2-D Array Arguments for MATLAB Functions

Some MATLAB functions accept a 2-D array as a single input argument and use the columns of the array separately. By default, if you pass a 2-D array to a MATLAB from Java, the array is split into separate arguments along the second dimension. To prevent this issue, cast the 2-D array to `Object`:

```
double[][] data = {{1.0, 2.0, 3.0}, {-1.0, -2.0, -3.0}};
HandleObject[] h = eng.feval("plot", (Object) data);
```

### Multidimensional Arrays

MATLAB and Java use different representations to display multidimensional arrays. However, indexing expressions produce the same results. For example, this example code defines an array with three dimensions in MATLAB. The array variable is then passed to Java and the results of indexed references are compared.

```
import com.mathworks.engine.*;
import java.io.StringWriter;
import java.util.Arrays;

public class ArrayIndexing {
    public static void main(String[] args) throws Exception {
        MatlabEngine eng = MatlabEngine.startMatlab();
        StringWriter writer = new StringWriter();
        eng.eval("A(1:2,1:3,1) = [1,2,3;4,5,6];");
        eng.eval("A(1:2,1:3,2) = [7,8,9;10,11,12]");
        double[][][] A = eng.getVariable("A");
        System.out.println("In Java: \n" + Arrays.deepToString(A));
        eng.eval("A(1,1,:) ", writer, null);
        System.out.println("A(1,1,:) " + writer.toString());
        System.out.println("Java [0][0][0] " + A[0][0][0]);
        System.out.println("Java [0][0][1] " + A[0][0][1]);
    }
}
```

```
}
```

Here is the program output showing how MATLAB and Java display the arrays. In MATLAB:

```
A(:,:,1) =
```

```
    1    2    3
    4    5    6
```

```
A(:,:,2) =
```

```
    7    8    9
   10   11   12
```

In Java:

```
[[[1.0, 7.0], [2.0, 8.0], [3.0, 9.0]], [[4.0, 10.0], [5.0, 11.0], [6.0, 12.0]]]
```

Here are the results showing indexed reference to the first element in each outer dimension:

```
A(1,1,:)
```

```
ans(:,:,1) =
```

```
    1
```

```
ans(:,:,2) =
```

```
    7
```

```
Java [0][0][0] 1.0
```

```
Java [0][0][1] 7.0
```

In MATLAB and Java, the results of the indexed expression are the same.

## Related Examples

- “Multidimensional Arrays”

## Incorrect Java Data Types

### In this section...

“Java String to MATLAB Character Vector” on page 8-45

“Setting Graphics Object Properties from Java” on page 8-46

“Java Integer to MATLAB double” on page 8-46

## Java String to MATLAB Character Vector

### Struct of Character Vectors

Some MATLAB functions accept a `struct` of name-value pairs as input arguments. The MATLAB Engine API for Java provides the `com.mathworks.matlab.engine.Struct` class to create this data structure in Java and pass it to MATLAB, where it is converted to a MATLAB `struct`.

Some MATLAB functions that accept `struct` input require field values to be MATLAB character vectors (`char`) instead of MATLAB strings (`string`). To create a Java `Struct` with the correct type of values, convert from `String` to `char` array before passing the variable to MATLAB.

You can use the `toCharArray` method for the conversion:

```
char[] on = "on".toCharArray();
char[] yOut = "yOut".toCharArray();
char[] tOut = "tOut".toCharArray();
Struct simParam = new Struct("SaveOutput", on, "OutputSaveName",
    yOut, "SaveTime", on, "TimeSaveName", tOut);
```

### String Argument to Character Vector

When MATLAB functions require `char` inputs, you can convert the Java `String` in the function call passed to MATLAB. For example, the MATLAB `eval` function requires `char` input:

```
double result = engine.feval("eval", "3+5");
Undefined function 'eval' for input arguments of type 'string'..
```

Passing a `char` array works correctly.

```
double result = engine.feval("eval", "3+5".toCharArray());
```

## Setting Graphics Object Properties from Java

You can set the values of MATLAB graphics object properties using the handle of the object. Pass the property names and property values as Java `char` arrays when passing to MATLAB functions.

```
double[][] data = {{1.0, 2.0, 3.0}, {-1.0, -2.0, -3.0}};
HandleObject[] h = eng.feval("plot", (Object)data);
String property = ("HitTest");
String value = ("off");
eng.feval(0,"set", h, property.toCharArray(), value.toCharArray());
```

## Java Integer to MATLAB double

Some MATLAB functions, such as `sqrt` restrict the input to `double` or `single` precision values. The MATLAB engine converts Java integers to MATLAB `int32` values. For MATLAB functions that do not accept integer values, ensure that you pass appropriate numeric values.

```
double result = engine.feval("sqrt", 4);
Undefined function 'sqrt' for input arguments of type 'int32'.
```

Passing a double works correctly.

```
double result = engine.feval("sqrt", 4.0);
```

## Related Examples

- “Java Data Type Conversions” on page 8-11

## Incorrect Number of Output Arguments

By default, the `feval` and `fevalAsync` methods request one output argument when calling MATLAB functions. Some MATLAB functions behave differently depending on the number of output arguments requested. Use the first input argument to specify the number of required output arguments as follows:

- If you want to call the function with no outputs, specify the first argument as `0`
- If you want to call the function with more than one output, specify the exact number.

For example, the MATLAB `disp` function does not return an output argument. This call to `disp` requires one output argument:

```
engine.feval("disp", 100);  
Error using disp  
Too many output arguments.
```

You must specify the number of output arguments explicitly as `0`:

```
engine.feval(0, "disp", 100);
```

### Related Examples

- “Execute MATLAB Functions from Java” on page 8-19





# MATLAB Engine for Python Topics

---

- “Get Started with MATLAB Engine API for Python” on page 9-2
- “Install MATLAB Engine API for Python” on page 9-5
- “Install MATLAB Engine API for Python in Nondefault Locations” on page 9-6
- “Start and Stop MATLAB Engine for Python” on page 9-8
- “Connect Python to Running MATLAB Session” on page 9-10
- “Call MATLAB Functions from Python” on page 9-13
- “Call MATLAB Functions Asynchronously from Python” on page 9-15
- “Call User Script and Function from Python” on page 9-16
- “Redirect Standard Output and Error to Python” on page 9-18
- “Use MATLAB Handle Objects in Python” on page 9-19
- “Use MATLAB Engine Workspace in Python” on page 9-21
- “Pass Data to MATLAB from Python” on page 9-22
- “Handle Data Returned from MATLAB to Python” on page 9-24
- “MATLAB Arrays as Python Variables” on page 9-27
- “Use MATLAB Arrays in Python” on page 9-32
- “Sort and Plot MATLAB Data from Python” on page 9-34
- “Get Help for MATLAB Functions from Python” on page 9-38
- “Default Numeric Types in MATLAB and Python” on page 9-40
- “System Requirements for MATLAB Engine API for Python” on page 9-42
- “Limitations to MATLAB Engine API for Python” on page 9-44
- “Troubleshoot MATLAB Errors in Python” on page 9-45

## Get Started with MATLAB Engine API for Python

The MATLAB Engine API for Python provides a Python package named `matlab` that enables you to call MATLAB functions from Python. You install the package once, and then you can call the engine in your current or future Python sessions. For help on installing or starting the engine, refer to:

- “Install MATLAB Engine API for Python” on page 9-5
- “Start and Stop MATLAB Engine for Python” on page 9-8

The `matlab` package contains the following:

- The MATLAB Engine API for Python
- A set of MATLAB array classes in Python (see “MATLAB Arrays as Python Variables” on page 9-27)

The engine provides functions to call MATLAB, and the array classes provide functions to create MATLAB arrays as Python objects. You can create an engine and call MATLAB functions with `matlab.engine`. You can create MATLAB arrays in Python by calling constructors of an array type (for example, `matlab.double` to create an array of doubles). MATLAB arrays can be input arguments to MATLAB functions called with the engine.

The table shows the structure of the `matlab` package.

Package	Function or Class	Description
<code>matlab.engine</code>	<code>start_matlab()</code>	Python function to create a <code>MatlabEngine</code> object, and attach it to a new MATLAB process
<code>matlab.engine</code>	<code>MatlabEngine</code>	Python class to provide methods for calling MATLAB functions
<code>matlab.engine</code>	<code>FutureResult</code>	Python class to hold results from a MATLAB

Package	Function or Class	Description
		function called asynchronously
matlab	double	Python class to hold array of MATLAB type <code>double</code>
matlab	single	Python class to hold array of MATLAB type <code>single</code>
matlab	int8	Python class to hold array of MATLAB type <code>int8</code>
matlab	int16	Python class to hold array of MATLAB type <code>int16</code>
matlab	int32	Python class to hold array of MATLAB type <code>int32</code>
matlab	int64	Python class to hold array of MATLAB type <code>int64</code>
matlab	uint8	Python class to hold array of MATLAB type <code>uint8</code>
matlab	uint16	Python class to hold array of MATLAB type <code>uint16</code>
matlab	uint32	Python class to hold array of MATLAB type <code>uint32</code>
matlab	uint64	Python class to hold array of MATLAB type <code>uint64</code>

Package	Function or Class	Description
matlab	logical	Python class to hold array of MATLAB type <code>logical</code>
matlab	object	Python class to hold a handle to a MATLAB object

### More About

- “System Requirements for MATLAB Engine API for Python” on page 9-42

## Install MATLAB Engine API for Python

To start the MATLAB engine within a Python session, you first must install the engine API as a Python package. MATLAB provides a standard Python `setup.py` file for building and installing the engine using the `distutils` module. You can use the same `setup.py` commands to build and install the engine on Windows, Mac, or Linux systems.

Before you install, verify your Python and MATLAB configurations.

- Your system has a supported version of Python and MATLAB R2014b or later. To check that Python is installed on your system, run Python at the operating system prompt.
- Add the folder that contains the Python interpreter to your path, if it is not already there.
- Find the path to the MATLAB folder. Start MATLAB and type `matlabroot` in the command window. Copy the path returned by `matlabroot`.

To install the engine API, execute the following commands at the operating system prompt, where `matlabroot` is the path to the MATLAB folder. You might need administrator privileges to execute these commands. Alternatively, use one of the nondefault options described in “Install MATLAB Engine API for Python in Nondefault Locations” on page 9-6.

- On Windows systems —  

```
cd "matlabroot\extern\engines\python"  
python setup.py install
```
- On Mac or Linux systems —  

```
cd "matlabroot/extern/engines/python"  
python setup.py install
```

### More About

- “System Requirements for MATLAB Engine API for Python” on page 9-42
- “Install Supported Python Implementation” on page 1-3
- “Install MATLAB Engine API for Python in Nondefault Locations” on page 9-6

### External Websites

- Python 2.7 Documentation — Installing Python Modules

## Install MATLAB Engine API for Python in Nondefault Locations

### In this section...

“Build or Install in Nondefault Folders” on page 9-6

“Install Engine in Your Home Folder” on page 9-7

### Build or Install in Nondefault Folders

By default, the installer builds the engine API for Python in the `matlabroot\extern\engines\python` folder. The installer installs the engine in the default Python folder. If you do not have write permission for either or both of these folders, select one of the following nondefault options. If you install to another folder, update the PYTHONPATH variable.

Type the following commands at the operating system prompt.

#### Build in Nondefault Folder, Install in Default Folder

If you do not have write permission to build the engine in the MATLAB folder, use a nondefault folder, *builddir*.

```
cd "matlabroot\extern\engines\python"  
python setup.py build --build-base="builddir" install
```

#### Build in Default Folder, Install in Nondefault Folder

If you do not have write permission to install the engine in the default Python folder, use a nondefault folder, *installdir*.

```
cd "matlabroot\extern\engines\python"  
python setup.py install --prefix="installdir"
```

To include *installdir* in the search path for Python packages, add *installdir* to the PYTHONPATH environment variable.

#### Build and Install in Nondefault Folders

If you do not have write permission for both the MATLAB folder and the default Python folder, you can specify nondefault folders. Use *builddir* for the build folder and *installdir* for the install folder.

```
cd "matlabroot\extern\engines\python"  
python setup.py build --build-base="builddir" install --prefix="installdir"
```

## Install Engine in Your Home Folder

To install the engine API for your use only, use the `--user` option to install to your home folder.

```
cd "matlabroot\extern\engines\python"  
python setup.py install --user
```

When you install with `--user`, you do not need to add your home folder to `PYTHONPATH`.

## Related Examples

- “Install MATLAB Engine API for Python” on page 9-5

## More About

- “System Requirements for MATLAB Engine API for Python” on page 9-42

## Start and Stop MATLAB Engine for Python

### In this section...

“Start MATLAB Engine for Python” on page 9-8

“Run Multiple Engines” on page 9-8

“Stop Engine” on page 9-8

“Start Engine with Startup Options” on page 9-9

“Start Engine Asynchronously” on page 9-9

### Start MATLAB Engine for Python

- Start Python at the operating system prompt.
- Import the `matlab.engine` package into your Python session.
- Start a new MATLAB process by calling `start_matlab`. The `start_matlab` function returns a Python object, `eng`, which allows you to pass data and call functions executed by MATLAB.

```
import matlab.engine
eng = matlab.engine.start_matlab()
```

### Run Multiple Engines

Start each engine separately. Each engine starts and communicates with its own MATLAB process.

```
eng1 = matlab.engine.start_matlab()
eng2 = matlab.engine.start_matlab()
```

### Stop Engine

Call either the `exit` or the `quit` function.

```
eng.quit()
```

If you exit Python with an engine still running, Python automatically stops the engine and its MATLAB process.



## Start Engine with Startup Options

Start the engine and pass the options as an input argument string to `matlab.engine.start_matlab`. For example, start MATLAB with the desktop.

```
eng = matlab.engine.start_matlab("-desktop")
```

You can define multiple startup options with a single string. For example, start the desktop and set the numeric display format to `short`.

```
eng = matlab.engine.start_matlab("-desktop -r 'format short'")
```

You also can start the desktop after you start the engine.

```
import matlab.engine
eng = matlab.engine.start_matlab()
eng.desktop(nargout=0)
```

## Start Engine Asynchronously

Start the engine asynchronously. While MATLAB starts, you can enter commands at the Python command line.

```
import matlab.engine
future = matlab.engine.start_matlab(async=True)
```

Create the MATLAB instance so you can perform computations in MATLAB.

```
eng = future.result()
```

## See Also

`matlab.engine.start_matlab`

## More About

- “Specify Startup Options”
- “Commonly Used Startup Options”

## Connect Python to Running MATLAB Session

You can connect the MATLAB Engine for Python to a shared MATLAB session that is already running on your local machine. You also can connect to multiple shared MATLAB sessions from a single Python session. You can share a MATLAB session at any time during the session, or at start with a startup option.

### Connect to Shared MATLAB Session

First, convert your MATLAB session to a shared session. From MATLAB call `matlab.engine.shareEngine`.

```
matlab.engine.shareEngine
```

Start Python at the operating system prompt. Call `matlab.engine.connect_matlab` from Python to connect to the shared MATLAB session. You can call any MATLAB function from Python.

```
import matlab.engine
eng = matlab.engine.connect_matlab()
eng.sqrt(4.0)
```

```
2.0
```

You can connect to a shared session by name. To find the name of a shared session, call `matlab.engine.find_matlab` from Python.

```
matlab.engine.find_matlab()
```

```
('MATLAB_13232',)
```

`matlab.engine.find_matlab` returns a tuple with the names of all shared MATLAB sessions on your local machine. In this example `matlab.engine.shareEngine` gave the shared session the default name `MATLAB_13232`, where `13232` is the ID of the MATLAB process. The operating system gives the MATLAB session a different process ID whenever you start MATLAB.

Connect to the MATLAB session by name.

```
eng.quit()
newEngine = matlab.engine.connect_matlab('MATLAB_13232')
```

If you do not specify the name of a shared session, `matlab.engine.connect_matlab` connects to the first session named in the tuple returned by `matlab.engine.find_matlab`.

## Connect Asynchronously to Shared MATLAB Session

From MATLAB, convert your MATLAB session to a shared session.

```
matlab.engine.shareEngine
```

Start Python at the operating system prompt. Connect asynchronously to the shared MATLAB session.

```
import matlab.engine
future = matlab.engine.connect_matlab(async=True)
eng = future.result()
```

Call a MATLAB function from Python.

```
eng.sqrt(4.0)
```

```
2.0
```

## Connect to Multiple Shared MATLAB Sessions

You can connect to multiple shared MATLAB sessions from Python.

Start a second MATLAB session. From MATLAB call `matlab.engine.shareEngine`. Give a name to the second shared session. The name must be a valid MATLAB variable name. For information on valid variable names, see “Variable Names”.

```
matlab.engine.shareEngine('MATLABEngine2')
```

From Python find all shared MATLAB sessions.

```
import matlab.engine
matlab.engine.find_matlab()

('MATLAB_13232', 'MATLABEngine2')
```

Call `matlab.engine.connect_matlab` from Python to connect to the shared MATLAB sessions.

```
eng1 = matlab.engine.connect_matlab('MATLAB_13232')
```

```
eng2 = matlab.engine.connect_matlab('MATLABEngine2')
```

## Start Shared MATLAB Sessions with Startup Options

By default MATLAB sessions are not shared. However, you can start MATLAB as a shared session with a startup option.

Start shared MATLAB sessions at the operating system prompt.

```
matlab -r "matlab.engine.shareEngine"  
matlab -r "matlab.engine.shareEngine('MATLABEngine3')"
```

You can start a session with a default name, or give a name enclosed in single quotes.

## See Also

```
matlab.engine.connect_matlab | matlab.engine.engineName |  
matlab.engine.find_matlab | matlab.engine.isEngineShared |  
matlab.engine.shareEngine
```

## More About

- “Specify Startup Options”
- “Commonly Used Startup Options”

## Call MATLAB Functions from Python

### In this section...

“Return Output Argument from MATLAB Function” on page 9-13

“Return Multiple Output Arguments from MATLAB Function” on page 9-13

“Return No Output Arguments from MATLAB Function” on page 9-13

“Stop Execution of Function” on page 9-14

### Return Output Argument from MATLAB Function

You can call any MATLAB function directly and return the results to Python. For example, to determine if a number is prime, use the engine to call the `isprime` function.

```
import matlab.engine
eng = matlab.engine.start_matlab()
tf = eng.isprime(37)
print(tf)
```

```
True
```

### Return Multiple Output Arguments from MATLAB Function

When you call a function with the engine, by default the engine returns a single output argument. If you know that the function can return multiple arguments, use the `nargout` argument to specify the number of output arguments.

To determine the greatest common denominator of two numbers, use the `gcd` function. Set `nargout` to return the three output arguments from `gcd`.

```
import matlab.engine
eng = matlab.engine.start_matlab()
t = eng.gcd(100.0,80.0,nargout=3)
print(t)
```

```
(20.0, 1.0, -1.0)
```

### Return No Output Arguments from MATLAB Function

Some MATLAB functions return no output arguments. If the function returns no arguments, set `nargout` to 0.

Open the MATLAB Help browser from Python.

```
import matlab.engine
eng = matlab.engine.start_matlab()
eng.doc(nargout=0)
```

The MATLAB `doc` function opens the browser, but does not return output arguments. If you do not specify `nargout=0`, the engine raises an error.

## Stop Execution of Function

To stop execution of a MATLAB function press **Ctrl+C**. Control returns to Python.

## See Also

`matlab.engine.MatlabEngine` | `matlab.engine.FutureResult`

## Related Examples

- “Call MATLAB Functions Asynchronously from Python” on page 9-15
- “Call User Script and Function from Python” on page 9-16
- “Use MATLAB Arrays in Python” on page 9-32
- “Sort and Plot MATLAB Data from Python” on page 9-34

## Call MATLAB Functions Asynchronously from Python

This example shows how to call the MATLAB `sqrt` function asynchronously from Python and retrieve the square root later.

The engine calls MATLAB functions synchronously by default. Control returns to Python only when the MATLAB function finishes. But the engine also can call functions asynchronously. Control immediately returns to Python while MATLAB is still executing the function. The engine stores the result in a Python variable that can be inspected after the function finishes.

Use the `async` argument to call a MATLAB function asynchronously.

```
import matlab.engine
eng = matlab.engine.start_matlab()
future = eng.sqrt(4.0, async=True)
ret = future.result()
print(ret)
```

```
2.0
```

Use the `done` method to check if an asynchronous call finished.

```
tf = future.done()
print(tf)
```

```
True
```

To stop execution of the function before it finishes, call `future.cancel()`.

### See Also

`matlab.engine.MatlabEngine` | `matlab.engine.FutureResult`

### Related Examples

- “Call MATLAB Functions from Python” on page 9-13
- “Call User Script and Function from Python” on page 9-16

## Call User Script and Function from Python

This example shows how to call a MATLAB script to compute the area of a triangle from Python.

In your current folder, create a MATLAB script in a file named `triarea.m`.

```
b = 5;  
h = 3;  
a = 0.5*(b.* h)
```

After you save the file, start Python and call the script.

```
import matlab.engine  
eng = matlab.engine.start_matlab()  
eng.triarea(nargout=0)
```

```
a =  
  
    7.5000
```

Specify `nargout=0`. Although the script prints output, it returns no output arguments to Python.

Convert the script to a function and call the function from the engine. To edit the file, open the MATLAB editor.

```
eng.edit('triarea',nargout=0)
```

Delete the three statements. Then add a function declaration and save the file.

```
function a = triarea(b,h)  
a = 0.5*(b.* h);
```

Call the new `triarea` function from the engine.

```
ret = eng.triarea(1.0,5.0)  
print(ret)
```

```
2.5
```

The `triarea` function returns only one output argument, so there is no need to specify `nargout`.



## See Also

`matlab.engine.MatlabEngine` | `matlab.engine.FutureResult`

## Related Examples

- “Call MATLAB Functions from Python” on page 9-13

## Redirect Standard Output and Error to Python

This example shows how to redirect standard output and standard error from a MATLAB function to Python `StringIO` objects.

In Python 2.7, use the `StringIO` module to create `StringIO` objects. To capture a warning message from `dec2hex`, specify `stdout` and `stderr`.

```
import matlab.engine
eng = matlab.engine.start_matlab()
import StringIO
out = StringIO.StringIO()
err = StringIO.StringIO()
ret = eng.dec2hex(2**60, stdout=out, stderr=err)
print(out.getvalue())
```

Warning: At least one of the input numbers is larger than the largest integer-valued f

In Python 3.3 or higher, use the `io` module to create `StringIO` objects.

```
import matlab.engine
eng = matlab.engine.start_matlab()
import io
out = io.StringIO()
err = io.StringIO()
ret = eng.dec2base(2**60, 16, stdout=out, stderr=err)
```

`dec2base` raises an exception when an input argument is greater than  $2^{52}$ . Display the error message captured in `err`.

```
print(err.getvalue())
```

```
Error using dec2base (line 22)
First argument must be an array of integers, 0 <= D <= 2^52.
```

### See Also

`matlab.engine.MatlabEngine` | `matlab.engine.FutureResult`

### Related Examples

- “Call MATLAB Functions from Python” on page 9-13

## Use MATLAB Handle Objects in Python

This example shows how to create an object from a MATLAB handle class and call its methods in Python.

In your current folder, create a MATLAB handle class in a file named `Triangle.m`.

```
classdef Triangle < handle
    properties (SetAccess = private)
        Base = 0;
        Height = 0;
    end

    methods
        function TR = Triangle(b,h)
            TR.Base = b;
            TR.Height = h;
        end

        function a = area(TR)
            a = 0.5 .* TR.Base .* TR.Height;
        end

        function setBase(TR,b)
            TR.Base = b;
        end

        function setHeight(TR,h)
            TR.Height = h;
        end
    end
end
```

Start Python. Create a `Triangle` handle object and call its `area` method with the engine. Pass the handle object as the first positional argument.

```
import matlab.engine
eng = matlab.engine.start_matlab()
tr = eng.Triangle(5.0,3.0)
a = eng.area(tr)
print(a)
```

7.5

Copy `tr` to the MATLAB workspace. You can use `eval` to access the properties of a handle object from the workspace.

```
eng.workspace["wtr"] = tr
b = eng.eval("wtr.Base")
print(b)
```

5.0

Change the height with the `setHeight` method. If your MATLAB handle class defines get and set methods for properties, you can access properties without using the MATLAB workspace.

```
eng.setHeight(tr,8.0,nargout=0)
a = eng.area(tr)
print(a)
```

20.0

---

**Note:** `Triangle` class object `tr`, is a handle to the object, not a copy of the object. If you create `tr` in a function, it is only valid within the scope of the function.

---

### See Also

`matlab.engine.MatlabEngine` | `matlab.engine.FutureResult`

### Related Examples

- “Call MATLAB Functions from Python” on page 9-13

## Use MATLAB Engine Workspace in Python

This example shows how to add variables to the MATLAB engine workspace in Python.

When you start the engine, it provides an interface to a collection of all MATLAB variables. This collection, named `workspace`, is implemented as a Python dictionary that is attached to the engine. The name of each MATLAB variable becomes a key in the `workspace` dictionary. The keys in `workspace` must be valid MATLAB identifiers (e.g., you cannot use numbers as keys). You can add variables to the engine workspace in Python, and then you can use the variables in MATLAB functions.

Add a variable to the engine workspace.

```
import matlab.engine
eng = matlab.engine.start_matlab()
x = 4.0
eng.workspace['y'] = x
a = eng.eval('sqrt(y)')
print(a)
```

```
2.0
```

In this example, `x` exists only as a Python variable. Its value is assigned to a new entry in the engine workspace, called `y`, creating a MATLAB variable. You can then call the MATLAB `eval` function to execute the `sqrt(y)` statement in MATLAB and return the output value, 2.0, to Python.

### See Also

`matlab.engine.MatlabEngine` | `matlab.engine.FutureResult`

### Related Examples

- “Call MATLAB Functions from Python” on page 9-13
- “Sort and Plot MATLAB Data from Python” on page 9-34

## Pass Data to MATLAB from Python

### In this section...

“Python Type to MATLAB Scalar Type Mapping” on page 9-22

“Python Container to MATLAB Array Type Mapping” on page 9-22

“Unsupported Python Types” on page 9-23

### Python Type to MATLAB Scalar Type Mapping

When you pass Python data as input arguments to MATLAB functions, the MATLAB Engine for Python converts the data into equivalent MATLAB data types.

Python Input Argument Type — Scalar Values Only	Resulting MATLAB Data Type
float	double
complex	Complex double
int	int64
long (Python 2.7 only)	int64
float(nan)	NaN
float(inf)	Inf
bool	logical
str	char
unicode (Python 2.7 only)	char
dict	Structure if all keys are strings not supported otherwise

### Python Container to MATLAB Array Type Mapping

Python Input Argument Type — Container	Resulting MATLAB Data Type
matlab numeric array object (see “MATLAB Arrays as Python Variables” on page 9-27)	Numeric array

Python Input Argument Type — Container	Resulting MATLAB Data Type
bytearray	uint8 array
bytes (Python 3.3 and higher)	uint8 array
bytes (Python 2.7)	char array
list	Cell array
set	Cell array
tuple	Cell array

## Unsupported Python Types

The following Python types are not supported by the MATLAB Engine API for Python:

- `array.array` (use MATLAB numeric array objects instead; see “MATLAB Arrays as Python Variables” on page 9-27)
- `None`
- `module.type` object

## More About

- “Handle Data Returned from MATLAB to Python” on page 9-24
- “Default Numeric Types in MATLAB and Python” on page 9-40
- “MATLAB Arrays as Python Variables” on page 9-27

## Handle Data Returned from MATLAB to Python

### In this section...

“MATLAB Scalar Type to Python Type Mapping” on page 9-24

“MATLAB Array Type to Python Type Mapping” on page 9-25

“Unsupported MATLAB Types” on page 9-25

### MATLAB Scalar Type to Python Type Mapping

When MATLAB functions return output arguments, the MATLAB Engine API for Python converts the data into equivalent Python data types.

MATLAB Output Argument Type — Scalar Values Only	Resulting Python Data Type
double	float
single	float
Complex (any numeric type)	complex
int8	int
uint8	int
int16	int
uint16	int
int32	int
uint32	int (Python 3.3 and higher) long (Python 2.7)
int64	int (Python 3.3 and higher) long (Python 2.7)
uint64	int (Python 3.3 and higher) long (Python 2.7)
NaN	float(nan)
Inf	float(inf)
logical	bool
char returned to Python 3.3 or higher	str



MATLAB Output Argument Type — Scalar Values Only	Resulting Python Data Type
char returned to Python 2.7	str (when MATLAB char value is less than or equal to <code>intmax('uint8')</code> ) unicode (when MATLAB char value is greater than <code>intmax('uint8')</code> )
Structure	dict
MATLAB handle object (such as the <code>containers.Map</code> type)	matlab.object  MATLAB returns a reference to a <code>matlab.object</code> , not the object itself. You cannot pass a <code>matlab.object</code> between MATLAB sessions.

## MATLAB Array Type to Python Type Mapping

MATLAB Output Argument Type — Array	Resulting Python Data Type
Numeric array	matlab numeric array object (see “MATLAB Arrays as Python Variables” on page 9-27)
char array (1-by-N, N-by-1) returned to Python 3.3 or higher	str
char array (1-by-N, N-by-1) returned to Python 2.7	str (when MATLAB char array has values less than or equal to <code>intmax('uint8')</code> ) unicode (when MATLAB char array has any value greater than <code>intmax('uint8')</code> )
Row or column cell array	list

## Unsupported MATLAB Types

The following MATLAB data types are not supported by the MATLAB Engine API for Python:

- Categorical array

- char array (M-by-N)
- Cell array (M-by-N)
- Function handle
- Sparse array
- Structure array
- Table
- MATLAB value objects (for a discussion of handle and value classes see “Comparison of Handle and Value Classes”)
- Non-MATLAB objects (such as Java objects)

### **More About**

- “Pass Data to MATLAB from Python” on page 9-22

## MATLAB Arrays as Python Variables

### In this section...

“Create MATLAB Arrays in Python” on page 9-27

“MATLAB Array Attributes and Methods in Python” on page 9-29

“Multidimensional MATLAB Arrays in Python” on page 9-29

“Index Into MATLAB Arrays in Python” on page 9-29

“Slice MATLAB Arrays in Python” on page 9-30

“Reshape MATLAB Arrays in Python” on page 9-31

The `matlab` Python package provides array classes to represent arrays of MATLAB numeric types as Python variables so that MATLAB arrays can be passed between Python and MATLAB.

### Create MATLAB Arrays in Python

You can create MATLAB numeric arrays in a Python session by calling constructors from the `matlab` Python package (for example, `matlab.double`, `matlab.int32`). The name of the constructor indicates the MATLAB numeric type.

You can use custom types for initializing MATLAB double arrays in Python. The custom type should inherit from the Python Abstract Base Class `collections.Sequence` to be used as an initializer.

You can pass MATLAB arrays as input arguments to functions called with the MATLAB Engine API for Python. When a MATLAB function returns a numeric array as an output argument, the engine returns the array to Python.

You can initialize the array with an optional `initializer` input argument that contains numbers. `initializer` must be a Python sequence type such as a `list`, `tuple`, or other sequence type. The optional `size` input argument sets the array size from a sequence. You can create multidimensional arrays by specifying `initializer` to contain multiple sequences of numbers, or by specifying `size` to be multidimensional. You can create a MATLAB array of complex numbers by setting the optional `is_complex` input argument to `True`. The `matlab` package provides the MATLAB array constructors listed in the table.

matlab Class	Constructor Call in Python
<code>matlab.double</code>	<code>matlab.double(initializer=None, size=None, is_complex=False)</code>
<code>matlab.single</code>	<code>matlab.single(initializer=None, size=None, is_complex=False)</code>
<code>matlab.int8</code>	<code>matlab.int8(initializer=None, size=None, is_complex=False)</code>
<code>matlab.int16</code>	<code>matlab.int16(initializer=None, size=None, is_complex=False)</code>
<code>matlab.int32</code>	<code>matlab.int32(initializer=None, size=None, is_complex=False)</code>
<code>matlab.int64<sup>a</sup></code>	<code>matlab.int64(initializer=None, size=None, is_complex=False)</code>
<code>matlab.uint8</code>	<code>matlab.uint8(initializer=None, size=None, is_complex=False)</code>
<code>matlab.uint16</code>	<code>matlab.uint16(initializer=None, size=None, is_complex=False)</code>
<code>matlab.uint32</code>	<code>matlab.uint32(initializer=None, size=None, is_complex=False)</code>
<code>matlab.uint64<sup>b</sup></code>	<code>matlab.uint64(initializer=None, size=None, is_complex=False)</code>
<code>matlab.logical</code>	<code>matlab.logical(initializer=None, size=None)<sup>c</sup></code>
<code>matlab.object</code>	No constructor. When a function returns a handle to a MATLAB object, the engine returns a <code>matlab.object</code> to Python.

- a. In Python 2.7 on Windows, `matlab.int64` is converted to `int32` in MATLAB. Also, MATLAB cannot return an `int64` array to Python.
- b. In Python 2.7 on Windows, `matlab.uint64` is converted to `uint32` in MATLAB. Also, MATLAB cannot return a `uint64` array to Python.
- c. Logicals cannot be made into an array of complex numbers.

When you create an array with N elements, the size is 1-by-N because it is a MATLAB array.

```
import matlab.engine
```

```
A = matlab.int8([1,2,3,4,5])
print(A.size)
```

```
(1, 5)
```

The initializer is a Python `list` containing five numbers. The MATLAB array size is 1-by-5, indicated by the tuple, `(1,5)`.

## MATLAB Array Attributes and Methods in Python

All MATLAB arrays created with `matlab` package constructors have the attributes and methods listed in this table.

Attribute or Method	Purpose
<code>size</code>	Size of array returned as a tuple
<code>reshape(size)</code>	Reshape array as specified by sequence <code>size</code>

## Multidimensional MATLAB Arrays in Python

In Python, you can create multidimensional MATLAB arrays of any numeric type. Use two Python `list` variables to create a 2-by-5 MATLAB array of doubles.

```
import matlab.engine
A = matlab.double([[1,2,3,4,5], [6,7,8,9,10]])
print(A)
```

```
[[1.0,2.0,3.0,4.0,5.0],[6.0,7.0,8.0,9.0,10.0]]
```

The `size` attribute of `A` shows that it is a 2-by-5 array.

```
print(A.size)
```

```
(2, 5)
```

## Index Into MATLAB Arrays in Python

You can index into MATLAB arrays just as you can index into Python `list` and `tuple` variables.

```
import matlab.engine
```

```
A = matlab.int8([1,2,3,4,5])
print(A[0])
```

```
[1,2,3,4,5]
```

The size of the MATLAB array is (1,5); therefore, A[0] is [1,2,3,4,5]. Index into the array to get 3.

```
print(A[0][2])
```

```
3
```

Python indexing is zero-based. When you access elements of MATLAB arrays in a Python session, use zero-based indexing.

Index into a multidimensional MATLAB array.

```
A = matlab.double([[1,2,3,4,5], [6,7,8,9,10]])
print(A[1][2])
```

```
8.0
```

## Slice MATLAB Arrays in Python

You can slice MATLAB arrays the same way you slice Python `list` and `tuple` variables.

```
import matlab.engine
A = matlab.int8([1,2,3,4,5])
print(A[0][1:4])
```

```
[2,3,4]
```

You can assign data to a slice. This code shows assignment from a Python `list` to a slice of an array.

```
A = matlab.double([[1,2,3,4], [5,6,7,8]]);
A[0] = [10,20,30,40]
print(A)
```

```
[[10.0,20.0,30.0,40.0],[5.0,6.0,7.0,8.0]]
```

You can assign data from another MATLAB array, or from any Python iterable that contains numbers.

You can specify slices for assignment as shown here.

```
A = matlab.int8([1,2,3,4,5,6,7,8]);
A[0][2:4] = [30,40]
A[0][6:8] = [70,80]
print(A)

[[1,2,30,40,5,6,70,80]]
```

---

**Note:** Slicing MATLAB arrays behaves differently from slicing a Python `list`. Slicing a MATLAB array returns a view instead of a shallow copy.

Given a MATLAB array and a Python `list` with the same values, assigning a slice results in different results as shown by the following code.

```
A = matlab.int32([[1,2],[3,4],[5,6]])
L = [[1,2],[3,4],[5,6]]
A[0] = A[0][::-1]
L[0] = L[0][::-1]
print(A)

[[2,2],[3,4],[5,6]]

print(L)

[[2, 1], [3, 4], [5, 6]]
```

---

## Reshape MATLAB Arrays in Python

You can reshape a MATLAB array in Python with the `reshape` method. Input argument `size` must be a sequence that preserves the number of elements. Use `reshape` to change a 1-by-9 MATLAB array to 3-by-3.

```
import matlab.engine
A = matlab.int8([1,2,3,4,5,6,7,8,9])
A.reshape((3,3))
print(A)

[[1,4,7],[2,5,8],[3,6,9]]
```

## Related Examples

- “Use MATLAB Arrays in Python” on page 9-32

## Use MATLAB Arrays in Python

This example shows how to create a MATLAB array in Python and pass it as the input argument to the MATLAB `sqrt` function.

The `matlab` package provides constructors to create MATLAB arrays in Python. The MATLAB Engine API for Python can pass such arrays as input arguments to MATLAB functions, and can return such arrays as output arguments to Python. You can create arrays of any MATLAB numeric or logical type from Python sequence types.

Create a MATLAB array from a Python `list`. Call the `sqrt` function on the array.

```
import matlab.engine
eng = matlab.engine.start_matlab()
a = matlab.double([1,4,9,16,25])
b = eng.sqrt(a)
print(b)
```

```
[[1.0,2.0,3.0,4.0,5.0]]
```

The engine returns `b`, which is a 1-by-5 `matlab.double` array.

Create a multidimensional array. The `magic` function returns a 2-D `matlab.double` array to Python. Use a `for` loop to print each row on a separate line. (Press **Enter** again when you see the `...` prompt to close the loop and print.)

```
a = eng.magic(6)
for x in a: print(x)
...

[35.0,1.0,6.0,26.0,19.0,24.0]
[3.0,32.0,7.0,21.0,23.0,25.0]
[31.0,9.0,2.0,22.0,27.0,20.0]
[8.0,28.0,33.0,17.0,10.0,15.0]
[30.0,5.0,34.0,12.0,14.0,16.0]
[4.0,36.0,29.0,13.0,18.0,11.0]
```

Call the `tril` function to get the lower triangular portion of `a`. Print each row on a separate line.

```
b = eng.tril(a)
for x in b: print(x)
...
```



```
[35.0,0.0,0.0,0.0,0.0,0.0]
[3.0,32.0,0.0,0.0,0.0,0.0]
[31.0,9.0,2.0,0.0,0.0,0.0]
[8.0,28.0,33.0,17.0,0.0,0.0]
[30.0,5.0,34.0,12.0,14.0,0.0]
[4.0,36.0,29.0,13.0,18.0,11.0]
```

## Related Examples

- “Call MATLAB Functions from Python” on page 9-13

## More About

- “MATLAB Arrays as Python Variables” on page 9-27

## Sort and Plot MATLAB Data from Python

This example shows how to sort data about patients into lists of smokers and nonsmokers in Python and plot blood pressure readings for the patients with MATLAB.

Start the engine, and read data about a set of patients into a MATLAB table. MATLAB provides a sample comma-delimited file, `patients.dat`, which contains information on 100 different patients.

```
import matlab.engine
eng = matlab.engine.start_matlab()
eng.eval("T = readtable('patients.dat');",nargout=0)
```

The MATLAB `readtable` function reads the data into a table. The engine does not support the MATLAB table data type. However, with the MATLAB `table2struct` function you can convert the table to a scalar structure, which is a data type the engine does support.

```
eng.eval("S = table2struct(T,'ToScalar',true);",nargout=0)
eng.eval("disp(S)",nargout=0)
```

```
        LastName: {100x1 cell}
           Gender: {100x1 cell}
             Age: [100x1 double]
        Location: {100x1 cell}
           Height: [100x1 double]
           Weight: [100x1 double]
            Smoker: [100x1 double]
        Systolic: [100x1 double]
        Diastolic: [100x1 double]
SelfAssessedHealthStatus: {100x1 cell}
```

You can pass `S` from the MATLAB workspace into your Python session. The engine converts `S` to a Python dictionary, `D`.

```
D = eng.workspace["S"]
```

`S` has fields that contain arrays. The engine converts cell arrays to Python `list` variables, and numeric arrays to MATLAB arrays. Therefore, `D["LastName"]` is of data type `list`, and `D["Age"]` is of data type `matlab.double`.

Sort blood pressure readings into lists of smokers and nonsmokers. In `patients.dat`, the column `Smoker` indicated a smoker with logical 1 (true), and a nonsmoker with a logical 0 (false). Convert `D["Smoker"]` to a `matlab.logical` array for sorting.

```
smoker = matlab.logical(D["Smoker"])
```

Convert the `Diastolic` blood pressure readings and `Smoker` indicators into 1-by-100 MATLAB arrays for sorting.

```
pressure = D["Diastolic"]
pressure.reshape((1,100))
pressure = pressure[0]
smoker.reshape((1,100))
smoker = smoker[0]
```

Sort the `pressure` array into lists of blood pressure readings for smokers and nonsmokers. Python list comprehensions provide a compact method for iterating over sequences. With the Python `zip` function, you can iterate over multiple sequences in a single `for` loop.

```
sp = [p for (p,s) in zip(pressure,smoker) if s is True]
nsp = [p for (p,s) in zip(pressure,smoker) if s is False]
```

Display the length of `sp`, the blood pressure readings for smokers in a `list`.

```
print(len(sp))
```

```
34
```

Display the length of `nsp`, the `list` of readings for nonsmokers.

```
print(len(nsp))
```

```
66
```

Calculate the mean blood pressure readings for smokers and nonsmokers. Convert `sp` and `nsp` to MATLAB arrays before passing them to the MATLAB `mean` function.

```
sp = matlab.double(sp)
nsp = matlab.double(nsp)
print(eng.mean(sp))
```

```
89.9117647059
```

Display the mean blood pressure for the nonsmokers.

```
print(eng.mean(nsp))
```

```
79.3787878788
```

Plot blood pressure readings for the smokers and nonsmokers. Call the MATLAB `linspace` function to define two  $x$ -axes for plotting. You can plot the 34 smokers and 66 nonsmokers on the same scatter plot.

```
sdx = eng.linspace(1.0,34.0,34)
nsdx = eng.linspace(1.0,34.0,66)
```

Show the axes boundaries with the `box` function.

```
eng.figure(nargout=0)
eng.hold("on",nargout=0)
eng.box("on",nargout=0)
```

You must call the `figure`, `hold`, and `box` functions with `nargout=0`, because these functions do not return output arguments.

Plot the blood pressure readings for the smokers and nonsmokers, and label the plot. For many MATLAB functions, the engine can return a handle to a MATLAB graphics object. You can store a handle to a MATLAB object in a Python variable, but you cannot manipulate the object properties in Python. You can pass MATLAB objects as input arguments to other MATLAB functions.


```
eng.scatter(sdx,sp,10,'blue')
<matlab.object object at 0x22d1510>
```

In the rest of this example, assign the output argument of MATLAB functions to `h` as a placeholder.

```
h = eng.scatter(nsdx,nsp,10,'red')
h = eng.xlabel("Patient (Anonymized)")
h = eng.ylabel("Diastolic Blood Pressure (mm Hg)")
h = eng.title("Blood Pressure Readings for All Patients")
h = eng.legend("Smokers","Nonsmokers")
```

Draw lines to show the average blood pressure readings for smokers and nonsmokers.

```
x = matlab.double([0,35])
y = matlab.double([89.9,89.9])
h = eng.line(x,y,"Color","blue")
h = eng.text(21.0,88.5,"89.9 (Smoker avg.)","Color","blue")
y = matlab.double([79.4,79.4])
h = eng.line(x,y,"Color","red")
h = eng.text(5.0,81.0,"79.4 (Nonsmoker avg.)","Color","red")
```



### See Also

readtable | scatter

## Get Help for MATLAB Functions from Python

In this section...
“How to Find MATLAB Help” on page 9-38
“Open MATLAB Help Browser from Python” on page 9-38
“Display MATLAB Help at Python Prompt” on page 9-39

### How to Find MATLAB Help

From Python, you can access supporting documentation for all MATLAB functions. This documentation includes examples and describes input arguments, output arguments, and calling syntax for each function.

The MATLAB Engine API for Python enables you to use the MATLAB `doc` and `help` functions. Use `doc` to open the MATLAB Help browser. Use `help` to get a brief description of a MATLAB function at the Python prompt.

### Open MATLAB Help Browser from Python

From Python, you can use the Help browser to open MATLAB function reference pages and search the documentation.

For example, display the reference page for the MATLAB `plot` function. (Since `doc` returns no output arguments, you must set `nargout=0`.)

```
import matlab.engine
eng = matlab.engine.start_matlab()
eng.doc("plot",nargout=0)
```

The reference page includes a description of the function, examples, and links to related documentation.

---

**Note:** Click an example title, or on the arrow next to a title, if you do not see the examples on a MATLAB reference page. Examples can be collapsed or expanded within a page.

---

If you call `eng.doc` with no positional arguments, it opens the Help browser. (You still must set the keyword argument `nargout=0`).

```
eng.doc(nargout=0)
```

To search the MATLAB documentation, type an expression in the search box at the top of any page in the Help browser. The browser returns a list of search results, highlighting words that match the expression.

Alternatively, you can search the documentation with the `docsearch` function. For example, search for pages that mention `plot`.

```
eng.docsearch("plot",nargout=0)
```

## Display MATLAB Help at Python Prompt

To display help text for a function at the Python prompt, call the MATLAB help function. For example, display the help text for `erf`.

```
import matlab.engine
eng = matlab.engine.start_matlab()
eng.help("erf",nargout=0)
```

```
ERF Error function.
```

```
Y = ERF(X) is the error function for each element of X. X must be
real. The error function is defined as:
```

```
erf(x) = 2/sqrt(pi) * integral from 0 to x of exp(-t^2) dt.
```

```
See also ERFC, ERFCX, ERFINV, ERFCINV.
```

```
Other functions named erf:
```

```
codistributed/erf
gpuArray/erf
sym/erf
```

```
Reference page in Help browser
doc erf
```

The output displays the help text, but does not include any links to help for other MATLAB functions that might be mentioned.

## Default Numeric Types in MATLAB and Python

MATLAB stores all numeric values as double-precision floating point numbers by default. This differs from Python, which stores some numbers as integers by default. Because of this difference, you might pass integers as input arguments to MATLAB functions that expect double-precision numbers.

Consider these variable assignments in MATLAB:

```
x = 4;  
y = 4.0;
```

Both `x` and `y` are of data type `double`. Now consider the same assignments in Python:

```
x = 4  
y = 4.0
```

`x` and `y` are of different numeric data types.

```
print(type(x))
```

```
<type 'int'>
```

```
print(type(y))
```

```
<type 'float'>
```

Most MATLAB functions take numeric input arguments of data type `double`. The best practice is to ensure that numbers you pass as input arguments to MATLAB functions are of Python data type `float`, not Python data type `int`. You can ensure that Python variables are floating point numbers if you:

- Make literals floating point numbers. For example, type `4.0` instead of `4`.
- Convert to data type `float`. For example, `x = float(4)` casts the number to data type `float`.
- Create a `matlab.double` array from a number or sequence. For example, `x = matlab.double([1,2,3,4,5])` creates an array of MATLAB data type `double` from a list of Python integers.

When you pass an integer to a MATLAB function that takes an input argument of data type `double`, the engine raises an error. See “MatlabExecutionError: Undefined Function” on page 9-45 for an example.



When you call a MATLAB function that does take integers as numeric input arguments, you can pass input arguments of Python data type `int` to the function.

## System Requirements for MATLAB Engine API for Python

In this section...
“Python Version Support” on page 9-42
“Download 64-Bit Versions of Python and MATLAB” on page 9-43
“Requirements for Building Python from Source” on page 9-43

You can use the MATLAB Engine API for Python on any platform that MATLAB supports.

### Python Version Support

To use the MATLAB Engine API for Python, you must have a supported version of the reference Python implementation (also known as CPython) installed on your system. The engine supports the following versions:

- version 2.7
- version 3.3
- version 3.4
- version 3.5

To download and install Python, see “Install Supported Python Implementation” on page 1-3.

---

**Note:** For 64-bit MATLAB on Microsoft Windows systems, select the 64-bit Python version, called Windows x86-64 MSI installer.

---

To call Python from your operating system prompt, either add the full path to Python to your PATH environment variable, or include the full path when you call the Python interpreter.

To determine if you are calling a supported version, type `python -V` at your operating system prompt to display the Python version number.

For help on the Python language, see [www.python.org/doc](http://www.python.org/doc) in the [python.org](http://python.org) documentation. For help on third-party or user-defined modules, refer to the product documentation.

## Download 64-Bit Versions of Python and MATLAB

The architecture of MATLAB must match the architecture of Python. On the Python download site, downloads for Microsoft Windows platforms are 32-bit versions by default. To download the 64-bit version, choose options with the name *Windows x86-64 MSI installer*.

To test whether your version of Python is 32-bit or 64-bit, type the following code at the Python prompt:

```
import sys
print(sys.maxsize > 2**32)
```

This code returns `True` if the Python interpreter is 64-bit, and `False` if it is 32-bit. (For more details, see Python 2.7 Documentation — Cross Platform.)

## Requirements for Building Python from Source

To enable wide-unicode support for Python 2.7 on Linux, configure the build with the `--enable-unicode=ucs4` option. This configure option is not needed when you build any version of Python on Mac systems, or Python 3.3 or higher on Linux.

## More About

- “Install Supported Python Implementation” on page 1-3

## External Websites

- [www.python.org/doc](http://www.python.org/doc)

## Limitations to MATLAB Engine API for Python

- The engine cannot start or connect to MATLAB on a remote machine.
- Python keyword arguments cannot be input arguments to MATLAB functions called with the engine. The engine passes only positional arguments to MATLAB functions.
- A recursive data structure cannot be passed as an input argument to a MATLAB function, or put into an engine workspace. (A recursive data structure is a Python data structure that includes itself as a value.)
- The MATLAB Engine API for Python is not thread-safe.

### More About

- “Troubleshoot MATLAB Errors in Python” on page 9-45

## Troubleshoot MATLAB Errors in Python

### In this section...

“MATLAB Errors in Python” on page 9-45

“MatlabExecutionError: Undefined Function” on page 9-45

“SyntaxError: Expression Not Valid Target” on page 9-46

“SyntaxError: Invalid Syntax” on page 9-46

“Cannot Find MATLAB Session in Python” on page 9-47

### MATLAB Errors in Python

When a MATLAB function raises an error, the MATLAB Engine for Python stops the function and catches the exception raised by MATLAB. The engine copies the error message to a new Python exception. The engine raises the Python exception.

If the Python interpreter catches the exception, the interpreter displays the error message that came from MATLAB. You also can handle exceptions raised by the engine in your Python code. See the `matlab.engine.MatlabEngine` and `matlab.engine.FutureResult` reference pages for the types of exceptions that the engine can raise.

### MatlabExecutionError: Undefined Function

Call the MATLAB `sqrt` function on an integer from Python. (This code sample omits the Python traceback and shows the error message only.)

```
import matlab.engine
eng = matlab.engine.start_matlab()
print(eng.sqrt(4))
```

```
matlab.engine.MatlabExecutionError: Undefined function 'sqrt' for input arguments of ty
```

MATLAB defines a `sqrt` function, but expects the input argument to be of data type `double`, not an integer. However, the input argument is 4, and before it is passed to MATLAB, Python interprets 4 as an integer. The engine converts the Python integer to an `int64` MATLAB data type.

MATLAB and Python define different default types for numbers. If you type `x = 4` at the MATLAB command line, `x` is a MATLAB `double`. If you type `x = 4` at the Python command line, `x` is a Python `int`.

To avoid this error, specify input arguments that are of Python data type `float`. The engine converts this type to MATLAB `double`.

```
print(eng.sqrt(4.0))
```

```
2.0
```

## SyntaxError: Expression Not Valid Target

You can call the MATLAB `eval` function from Python to create MATLAB variables. (This code sample omits the Python traceback and shows the error message only.)

```
import matlab.engine
eng = matlab.engine.start_matlab()
eng.eval("x = 4;")
```

```
SyntaxError: Error: The expression to the left of the equals sign is not a valid target
```

When the engine calls `eval`, it passes a statement to MATLAB for execution. When you do not specify the input argument `nargout` input argument, the engine expects one output argument. However, this MATLAB statement returns no output arguments.

To avoid this error, specify `nargout` as 0 whenever the MATLAB function you call returns no output arguments.

```
eng.eval("x = 4;", nargout=0)
```

## SyntaxError: Invalid Syntax

Call the MATLAB `print` function from Python 2.7 to print a plot you create with the MATLAB `surf` function.

```
import matlab.engine
eng = matlab.engine.start_matlab()
eng.eval("surf(peaks)", nargout=0)
eng.print("-djpeg", "surf", nargout=0)
```

```
File "<stdin>", line 1
    eng.print("-djpeg", "surf", nargout=0)
```

```

^
SyntaxError: invalid syntax
    
```

MATLAB and Python functions can have the same name. When this happens, the engine calls the MATLAB function.

However, the engine cannot directly call a MATLAB function that has a name that also is a reserved word in the Python language. For example, in Python 2.7, `print` is a reserved word. (In Python 3.3 and higher, the previous code runs because `print` is a built-in function, not a reserved word.)

To avoid this error, call the MATLAB function with `eval`.

```
eng.eval("print(' -djpeg ', 'surf ');", nargout=0)
```

If the MATLAB function is a function that you created, you can rename it so that its name is no longer a Python reserved word. The Python documentation lists reserved words:

- Python 2.7 reserved words ([https://docs.python.org/2/reference/lexical\\_analysis.html#keywords](https://docs.python.org/2/reference/lexical_analysis.html#keywords))
- Python 3.3 and higher reserved words ([https://docs.python.org/3/reference/lexical\\_analysis.html#keywords](https://docs.python.org/3/reference/lexical_analysis.html#keywords))

## Cannot Find MATLAB Session in Python

If you override the operating system `TEMP` or `TMP` environment variables in MATLAB, Python might not be able to connect to the MATLAB Engine for Python. For example, if you type the following at the Python prompt:

```
matlab.engine.find_matlab()
```

Python displays `()`.

MATLAB Engine for Python uses the `temp` folder to record information for shared MATLAB sessions. To work around this issue, make the following changes to the environment variables in Python. *temp\_folder* is the path to the folder which you set in MATLAB.

```
os.environ['TMP'] = r'temp_folder'
os.environ['TEMP'] = r'temp_folder'
eng=matlab.engine.find_matlab()
```

## **More About**

- “Limitations to MATLAB Engine API for Python” on page 9-44
- “Default Numeric Types in MATLAB and Python” on page 9-40



# Using Java Libraries from MATLAB

---

- “Call Method on Java Object” on page 10-2
- “Java Libraries” on page 10-3
- “Bring Java Classes into MATLAB Workspace” on page 10-5
- “Convert Java String to Uppercase” on page 10-12
- “Use Class in Java JAR File on Static Class Path” on page 10-13
- “Call User-Defined Java Class on Dynamic Class Path” on page 10-14
- “Java Objects” on page 10-15
- “Java Object Methods” on page 10-23
- “Java Arrays” on page 10-31
- “Read URL Using `java.net.URL`” on page 10-48
- “Find Internet Protocol Address Using `java.net.InetAddress`” on page 10-50
- “Create and Use Phone Book Using Java Classes” on page 10-53
- “Java Heap Memory Preferences” on page 10-65
- “Pass Data to Java Methods” on page 10-66
- “Handle Data Returned from Java Methods” on page 10-76

## Call Method on Java Object

MATLAB loads Java class definitions from files that are on the Java class path.

Use one of the following syntaxes to call `method` on Java object `obj`.

- MATLAB syntax:

```
package.class.method(obj, arg1, ..., argn)
```

- Java syntax:

```
obj.method(arg1, ..., argn)
```

- Use the following when the method name exceeds the maximum length of a MATLAB identifier.

```
javaMethod(method, obj, arg1, ..., argn)
```

You do not need to load or import the Java class. Use the MATLAB `import` function to simplify the Java class name in a command.

### See Also

`import` | `javaclasspath`

### More About

- “Java Class Path” on page 10-5
- “Simplifying Java Class Names Using `import` Function” on page 10-9

## Java Libraries

### In this section...

“Java Software Is Integral to MATLAB” on page 10-3

“When to Use Java Libraries in MATLAB” on page 10-3

“To Learn More About Java Programming Language” on page 10-4

“Platform Support for JVM Software” on page 10-4

### Java Software Is Integral to MATLAB

Every installation of MATLAB includes Java Virtual Machine (JVM) software. You can use the Java interpreter via MATLAB commands, and you can create and run programs that create and access Java objects.

From MATLAB, you can:

- Access Java API (application programming interface) class packages that support essential activities such as I/O and networking. For example, the `URL` class provides convenient access to resources on the Internet.
- Access third-party Java classes
- Easily construct Java objects in MATLAB workspace
- Call Java object methods, using either Java or MATLAB syntax
- Pass data between MATLAB variables and Java objects

### When to Use Java Libraries in MATLAB

The MATLAB Java interface is intended for MATLAB users who want to take advantage of the special capabilities of the Java programming language.

- You need to access, from MATLAB, the capabilities of available Java classes.
- You are familiar with object-oriented programming in Java or in another language, such as C++.
- You are familiar with the MATLAB Class System, or with “MEX File Creation API”.

### To Learn More About Java Programming Language

For a complete description of the Java language and for guidance in object-oriented software design and programming, consult outside resources.

### Platform Support for JVM Software

To find out which version of JVM software MATLAB uses on your platform, type the following at the MATLAB prompt:

```
version -java
```

### Related Examples

- “Convert Java String to Uppercase” on page 10-12
- “Call Method on Java Object” on page 10-2

## Bring Java Classes into MATLAB Workspace

### In this section...

“Introduction” on page 10-5

“Defining New Java Classes” on page 10-5

“Java Class Path” on page 10-5

“Making Java Classes Available in MATLAB Workspace” on page 10-7

“Loading Java Class Definitions” on page 10-9

“Simplifying Java Class Names Using import Function” on page 10-9

“Locating Native Method Libraries” on page 10-10

### Introduction

You can draw from an extensive collection of existing Java classes or create your own class definitions to use with MATLAB. This topic explains how to find the class definitions that you need or how to create classes of your own design. This topic also describes how to specify the native method libraries used by Java code.

### Defining New Java Classes

To define new Java classes and subclasses of existing classes, use a Java Development Kit external to MATLAB. For information on supported versions of JDK software, see the Supported and Compatible Compilers website.

After you create class definitions in `.java` files, use your Java compiler to produce `.class` files from them. The next step is to make the class definitions in those `.class` files available for you to use in MATLAB.

### Java Class Path

- “Static Path” on page 10-6
- “Dynamic Path” on page 10-7

MATLAB loads Java class definitions from files that are on the *Java class path*. The class path is a series of file and folder specifications that MATLAB uses to locate third-party and user-defined class definitions. When loading a Java class, MATLAB searches files

and folders in the order they occur on the class path. The search ends when MATLAB finds a file that contains the class definition.

MATLAB segments the Java class path into a static path and a dynamic path. MATLAB provides the dynamic path as a convenience for when you develop your own Java classes. After you develop and debug a Java class, add the class to the static path.

To view the two path segments, use the `javaclasspath` function.

### Static Path

Use the static path if you want the class functionality to run the same way it does in Java. Also, the static path offers better class loading performance than the dynamic path.

To add files to the static path, create a `javaclasspath.txt` file:

- 1 Create an ASCII text file and name the file `javaclasspath.txt`.
- 2 Enter the name of a Java class folder or jar file, one per line. For example:  

```
c:\work\javaclasses
```
- 3 To simplify folder specifications in cross-platform environments, use these macros: `$matlabroot`, `$arch`, and `$jre_home`.
- 4 Save the file in your preferences folder. To view the location of the preferences folder, type:

```
prefdir
```

Alternatively, save the `javaclasspath.txt` file in your MATLAB startup folder. Classes specified in this file override classes specified in the `javaclasspath.txt` file in the preferences folder.

- 5 Restart MATLAB.

MATLAB reads the static class path only at startup. If you edit `javaclasspath.txt` or change your `.class` files while MATLAB is running, restart MATLAB to put those changes into effect.

If you do not want MATLAB to use the entries in the `javaclasspath.txt` file, start MATLAB with the `-nouserjavapath` option.

---

**Note:** Do not put Java classes on the static path if they have dependencies on classes on the dynamic path.

---

## Dynamic Path

You can change class definitions on the dynamic path without restarting MATLAB. Therefore, it is useful to put a user-defined Java class definition on the dynamic path while you develop and debug the class.

MATLAB always searches the static path before the dynamic path.

To add a class to the dynamic path, use the `javaclasspath` and `javaaddpath` functions. To remove an entry, use the `javarmpath` function. These functions clear all existing variables and global variables in the workspace.

The dynamic path offers greater flexibility in changing the path. However, Java classes on the dynamic path might load more slowly than classes on the static path. Also, classes on the dynamic path might not behave identical to classes on the static path. If your class does not behave as expected, use the static path.

After developing a Java class, put the class on the static path.

## Making Java Classes Available in MATLAB Workspace

To make third-party and user-defined Java classes available to MATLAB, place them on either the static or dynamic Java class path.

- “Making Individual (Unpackaged) Classes Available” on page 10-7
- “Making Entire Packages Available” on page 10-8
- “Making Classes in a JAR File Available” on page 10-8
- “Loading a Class Using Java `Class.forName` Method” on page 10-8

### Making Individual (Unpackaged) Classes Available

You can use individual classes (classes that are not part of a package) in MATLAB. To make them available, specify the full path to the folder you want to use for the `.class` files.

For example, to make available your compiled Java classes in the file `d:\work\javaclasses\test.class`, add the following entry to the static or dynamic class path:

```
d:\work\javaclasses
```

To put this folder on the static class path, edit the `javaclasspath.txt` file.

To put this folder on the dynamic class path, use the following command:

```
javaaddpath d:\work\javaclasses
```

### **Making Entire Packages Available**

You can access classes in a package. To make a package available to MATLAB, specify the full path to the *parent folder of the highest level folder* of the package path. This folder is the first component in the package name.

For example, if your Java class package `com.mw.tbx.ini` has its classes in folder `d:\work\com\mw\tbx\ini`, add the following folder to your static or dynamic class path:

```
d:\work
```

### **Making Classes in a JAR File Available**

You can use the `jar` (Java Archive) tool to create a JAR file, containing multiple Java classes and packages in a compressed ZIP format. For information on `jar` and JAR files, consult your Java development documentation.

To make the contents of a JAR file available for use in MATLAB, specify the full path, *including full file name*, for the JAR file. You also can put the JAR file on the MATLAB path.

---

**Note:** The path requirement for JAR files is different from the requirement for `.class` files and packages, for which you do not specify any file name.

---

For example, to make available the JAR file `e:\java\classes\utilpkg.jar`, add the following file specification to your static or dynamic class path:

```
e:\java\classes\utilpkg.jar
```

You can now call the public methods in the JAR file. For information about these methods, refer to the JAR file documentation.

### **Loading a Class Using Java Class.forName Method**

Use the `javaObjectEDT` function instead of the Java `Class.forName` method. For example, replace the following statement:



```
java.lang.Class.forName('xyz.myapp.MyClass')
```

with:

```
javaObjectEDT('xyz.myapp.MyClass')
```

## Loading Java Class Definitions

Normally, MATLAB loads a Java class automatically when your code first uses it, for example, when you call its constructor. However, be aware of the following exception. When you use the `which` function on methods defined by Java classes, the function only acts on the classes currently *loaded* into the MATLAB workspace. In contrast, `which` always operates on MATLAB classes, whether they are loaded.

## Determining Which Classes Are Loaded

At any time during a MATLAB session, you can obtain a listing of all the Java classes that are currently loaded. To do so, use the `inmem` function as follows:

```
[M,X,J] = inmem
```

This function returns the list of Java classes in the output argument `J`. (It also returns the names of all currently loaded MATLAB functions in `M`, and the names of all currently loaded MEX-files in `X`.)

Here is a sample of output from the `inmem` function:

```
[m,x,j] = inmem;  
j
```

MATLAB displays:

```
j =  
'java.util.Date'  
'com.mathworks.ide.desktop.MLDesktop'
```

## Simplifying Java Class Names Using `import` Function

Your MATLAB commands can refer to any Java class by its fully qualified name, which includes its package name. For example, the following are fully qualified names:

- `java.lang.String`

- `java.util.Enumeration`

A fully qualified name can be long, making commands and functions, such as constructors, cumbersome to edit and to read. To refer to classes by the class name alone (without a package name), first import the fully qualified name into MATLAB.

MATLAB adds all classes that you import to a list called the *import list*. To see what classes are on that list, type `import`. Your code can refer to any class on the list by class name alone.

When called from a function, `import` adds the specified classes to the import list in effect for that function. When invoked at the command prompt, `import` uses the base import list for your MATLAB platform.

For example, suppose that a function contains the following statements:

```
import java.lang.String
import java.util.* java.awt.*
import java.util.Enumeration
```

Any code that follows these `import` statements can refer to the `String`, `Frame`, and `Enumeration` classes without using the package names. For example:

```
str = String('hello');      % Create java.lang.String object
frm = Frame;                % Create java.awt.Frame object
methods Enumeration        % List java.util.Enumeration methods
```

To remove the list of imported Java classes, type:

```
clear import
```

## Locating Native Method Libraries

Java classes can dynamically load native methods using the Java method `java.lang.System.loadLibrary("LibFile")`. In order for the JVM software to locate the specified library file, the folder containing it must be on the Java Library Path. This path is established when the MATLAB runs the JVM software at startup.

You can augment the search path for native method libraries by creating an ASCII text file named `javalibrarypath.txt` in your preferences folder. Follow these guidelines when editing this file:

- Specify each new folder on a line by itself.

- Specify only the folder names, not the names of the DLL files. The `loadLibrary` call reads the file names.
- To simplify the specification of directories in cross-platform environments, use any of these macros: `$matlabroot`, `$arch`, and `$jre_home`.

You also can create a `javalibrarypath.txt` file in your MATLAB startup folder. Libraries specified in this file override libraries specified in the `javalibrarypath.txt` file in the preferences folder.

To disable using the `javalibrarypath.txt` file, execute MATLAB with the `-nouserjavapath` option.

## See Also

`import` | `inmem` | `javaclasspath`

## Related Examples

- “Use Class in Java JAR File on Static Class Path” on page 10-13
- “Call User-Defined Java Class on Dynamic Class Path” on page 10-14

## Convert Java String to Uppercase

This example shows how to call a built-in Java String class method, `toUpperCase`.

Create a Java string using the built-in class `java.lang.String`.

```
str = java.lang.String('hello');
```

Display methods for the string.

```
methods(str)
```

```
Methods for class java.lang.String:
```

<code>String</code>	<code>getBytes</code>	<code>replaceAll</code>
<code>charAt</code>	<code>getChars</code>	<code>replaceFirst</code>
<code>codePointAt</code>	<code>getClass</code>	<code>split</code>
<code>codePointBefore</code>	<code>hashCode</code>	<code>startsWith</code>
<code>codePointCount</code>	<code>indexOf</code>	<code>subSequence</code>
<code>compareTo</code>	<code>intern</code>	<code>substring</code>
<code>compareToIgnoreCase</code>	<code>isEmpty</code>	<code>toCharArray</code>
<code>concat</code>	<code>lastIndexOf</code>	<code>toLowerCase</code>
<code>contains</code>	<code>length</code>	<code>toString</code>
<code>contentEquals</code>	<code>matches</code>	<code>toUpperCase</code>
<code>copyValueOf</code>	<code>notify</code>	<code>trim</code>
<code>endsWith</code>	<code>notifyAll</code>	<code>valueOf</code>
<code>equals</code>	<code>offsetByCodePoints</code>	<code>wait</code>
<code>equalsIgnoreCase</code>	<code>regionMatches</code>	
<code>format</code>	<code>replace</code>	

Call the `toUpperCase` method.

```
toUpperCase(str)
```

```
ans =
```

```
HELLO
```

## Use Class in Java JAR File on Static Class Path

This example shows how to call a class method in a Java Archive (JAR) file. The example uses a JAR file named *mylibrary.jar* in the folder `C:\Documents\MATLAB\`, containing a method, *package.class.mymethod(params)*. Substitute your own JAR file name and path, and read the documentation to call your own method.

This example puts the JAR file on the static Java class path, making the classes always available in MATLAB. If you only want to use the classes in the current MATLAB session, add the JAR file to the dynamic class path using the `javaaddpath` function.

Copy the *mylibrary.jar* file to the `C:\Documents\MATLAB\` folder.

Add the JAR file to the static class path. Open the `javaclasspath.txt` file.

```
cd(prefdir)
edit javaclasspath.txt
```

Add the following text on a new line in the file.

```
C:\Documents\MATLAB\mylibrary.jar
```

Save and close the file. From now on, the JAR file is available to MATLAB.

Restart MATLAB.

Call the method.

```
package.class.mymethod(params)
```

### See Also

[javaaddpath](#) | [javaclasspath](#)

### Related Examples

- “Call User-Defined Java Class on Dynamic Class Path” on page 10-14

### More About

- “Java Class Path” on page 10-5

## Call User-Defined Java Class on Dynamic Class Path

This example shows how to call a method in your own Java class. The example uses a class file named *myclass.class* in the folder `C:\Documents\MATLAB\`, containing a method, *package.myclass.mymethod(params)*. Substitute your own class file name and path, and call the method with the appropriate parameter list.

This example puts the class file on the dynamic Java class path, making the class available in the current MATLAB session only. MATLAB provides the dynamic path as a convenience for when you develop your own Java classes. To make the class always available in MATLAB, use the static class path by editing the `javaclasspath.txt` file in your `prefdir` folder.

Add the class to the dynamic Java class path.

```
javaaddpath('C:\Documents\MATLAB\')
```

To access the class, you must modify the Java path every time you start MATLAB.

Call the method.

```
package.myclass.mymethod(params)
```

### See Also

`javaaddpath` | `javaclasspath`

### Related Examples

- “Use Class in Java JAR File on Static Class Path” on page 10-13

### More About

- “Java Class Path” on page 10-5

# Java Objects

## In this section...

“Overview” on page 10-15

“Constructing Java Objects” on page 10-15

“Concatenating Java Objects” on page 10-17

“Saving and Loading Java Objects to MAT-Files” on page 10-18

“Finding the Public Data Fields of an Object” on page 10-19

“Accessing Private and Public Data” on page 10-20

“Determining the Class of an Object” on page 10-21

## Overview

You create a Java object in the MATLAB workspace by calling one of the constructors of that class. You then use commands and programming statements to perform operations on these objects. You also can save your Java objects to a MAT-file and, in subsequent sessions, reload them into MATLAB.

## Constructing Java Objects

You construct Java objects in the MATLAB workspace by calling the Java class constructor, which has the same name as the class. For example, the following constructor creates a `myDate` object:

```
myDate = java.util.Date
```

```
myDate =  
Thu Aug 23 12:58:54 EDT 2007
```

MATLAB displays information for your system.

## Using the `javaObjectEDT` Function

Under certain circumstances, use the `javaObjectEDT` function to construct a Java object. The following syntax invokes the Java constructor for class, `class_name`, with the argument list that matches `x1, . . . , xn`, and returns a new object, `J`.

```
J = javaObjectEDT('class_name',x1,...,xn);
```

For example, to construct and return a Java object of class `java.lang.String`, type:

```
jstr = javaObjectEDT('java.lang.String','hello');
```

With the `javaObjectEDT` function you can:

- Use classes that have names that exceed the maximum length of a MATLAB identifier. (Call the `namelengthmax` function to obtain the maximum identifier length.)
- Specify the class for an object at run time, for example, as input from an application user

The default MATLAB constructor syntax requires that no segment of the input class name can be longer than `namelengthmax` characters. (A *class name segment* is any portion of the class name before, between, or after a dot. For example, there are three segments in class, `java.lang.String`.) MATLAB truncates any class name segment that exceeds `namelengthmax` characters. In the rare case where you use a class name of this length, use `javaObjectEDT` to instantiate the class.

The `javaObjectEDT` function also allows you to specify the Java class for the object being constructed at run time. In this situation, you call `javaObjectEDT` with a character vector variable in place of the class name argument.

```
class = 'java.lang.String';  
text = 'hello';  
jstr = javaObjectEDT(class, text);
```

In the usual case, when the class to instantiate is known at development time, it is more convenient to use the MATLAB constructor syntax. For example, to create a `java.lang.String` object, type:

```
jstr = java.lang.String('hello');
```

Use the `javaObjectEDT` function instead of the Java `Class.forName` method. For example, replace the following statement:

```
java.lang.Class.forName('xyz.myapp.MyClass')
```

with:

```
javaObjectEDT('xyz.myapp.MyClass')
```



---

**Note:** Typically, you do not need to use `javaObjectEDT`. The default MATLAB syntax for instantiating a Java class is simpler and is preferable for most applications. Use `javaObjectEDT` primarily for the previously described cases.

---

### Java Objects Are References in MATLAB Applications

In MATLAB, Java objects are *references* and do not adhere to MATLAB copy-on-assignment and pass-by-value rules. For example:

```
myDate = java.util.Date;
setHours(myDate,10)
newDate = myDate;
```

In this example, the variable `newDate` is a reference to `myDate`, not a copy of the object. Any change to the object referenced by `newDate` also changes the object at `myDate`. Either MATLAB code or Java code might change the object.

The following example shows that `myDate` and `newDate` are references to the same object. When you change the hour via one reference (`newDate`), the change is reflected through the other reference (`myDate`), as well.

```
setHours(newDate,8)
getHours(myDate)
```

```
ans =
     8
```

### Concatenating Java Objects

You can concatenate Java objects in the same way that you concatenate native MATLAB types. You use either the `cat` function or the `[]` operators to tell MATLAB to assemble the enclosed objects into a single object.

#### Concatenating Objects of the Same Class

If concatenate objects of the same Java class, the concatenation is an array of objects from the same class.

In the following example, the `cat` function concatenates two objects of the class `java.awt.Integer`. The class of the result is also `java.awt.Integer`.

```
value1 = java.lang.Integer(88);
value2 = java.lang.Integer(45);
```

```
cat(1, value1, value2)

ans =
java.lang.Integer[]:
    [88]
    [45]
```

### Concatenating Objects of Unlike Classes

If you concatenate objects of unlike classes, MATLAB finds one class from which all of the input objects inherit. The concatenation is an instance of this class. MATLAB selects the lowest common parent in the Java class hierarchy as the output class.

For example, concatenating objects of `java.lang.Byte`, `java.lang.Integer`, and `java.lang.Double` creates an object of the common parent to the three input classes, `java.lang.Number`.

```
byte = java.lang.Byte(127);
integer = java.lang.Integer(52);
double = java.lang.Double(7.8);
[byte integer double]

ans =
java.lang.Number[]:
    [ 127]
    [ 52]
    [7.8000]
```

If there is no common, lower-level parent, then the resultant class is `java.lang.Object`, which is the root of the entire Java class hierarchy.

```
byte = java.lang.Byte(127);
point = java.awt.Point(24,127);
[byte point]

ans =
java.lang.Object[]:
    [ 127]
    [1x1 java.awt.Point]
```

### Saving and Loading Java Objects to MAT-Files

Use the `save` function to save a Java object to a MAT-file. To load it back into MATLAB from that MAT-file, use the `load` function. When you save or load a Java object, the object and its class must meet all of the following criteria.

- The class implements the `Serializable` interface (part of the Java API), either directly or by inheriting it from a parent class. Any embedded or otherwise referenced objects must also implement `Serializable`.
- The definition of the class is not changed between saving and loading the object. Any change to the data fields or methods of a class prevents the loading (deserialization) of an object that was constructed with the old class definition.
- Either the class does not have any transient data fields, or the values in transient data fields of the object to be saved are not significant. Values in transient data fields are never saved with the object.

If you define your own Java classes, or subclasses of existing classes, follow this criteria to enable saving and loading objects of the class in MATLAB. For details on defining classes to support serialization, consult your Java development documentation.

## Finding the Public Data Fields of an Object

To list the public fields that belong to a Java object, use the `fieldnames` function, which takes either of these forms.

```
names = fieldnames(obj)
names = fieldnames(obj, '-full')
```

Calling `fieldnames` without `-full` returns the names of all the data fields (including inherited) on the object. With the `-full` qualifier, `fieldnames` returns the full description of the data fields defined for the object, including type, attributes, and inheritance information.

For example, create an `Integer` object with the command:

```
value = java.lang.Integer(0);
```

To see a full description of the data fields of `value`, type:

```
fieldnames(value, '-full')

ans =
    'static final int MIN_VALUE'
    'static final int MAX_VALUE'
    'static final java.lang.Class TYPE'
    'static final int SIZE'
```

## Accessing Private and Public Data

Java API classes provide accessor methods you can use to read from and, where allowed, to modify *private* data fields. These methods are sometimes referred to as *get* and *set* methods, respectively.

Some Java classes have *public* data fields, which your code can read or modify directly. To access these fields, use the syntax `object.field`.

### Examples

The `java.awt.Frame` class provides an example of access to both private and public data fields. This class has the read accessor method `getSize`, which returns a `java.awt.Dimension` object. The `Dimension` object has data fields `height` and `width`, which are public and therefore directly accessible. For example, to access this data, type:

```
frame = java.awt.Frame;  
frameDim = getSize(frame);  
height = frameDim.height;  
frameDim.width = 42;
```

The sample code for “Find Internet Protocol Address Using `java.net.InetAddress`” on page 10-50 uses calls to data field accessors on a `java.net.InetAddress` object.

```
hostname = address.getHostName;  
ipaddress = address.getHostAddress;
```

### Accessing Data from a Static Field

In a Java language program, a *static data field* is a field that applies to an entire class of objects. Static fields are most commonly accessed in relation to the class name itself. For example, the following code accesses the `TYPE` field of the `Integer` class using the package and class names, `java.lang.Integer`.

```
thisType = java.lang.Integer.TYPE;
```

In MATLAB, you can use that same syntax. Or you can refer to the `TYPE` field as an instance of the class. The following example creates an instance of `java.lang.Integer` called `value`, and then accesses the `TYPE` field using the name `value` rather than the package and class names.

```
value = java.lang.Integer(0);  
thatType = value.TYPE
```

```
thatType =  
int
```

### Assigning to a Static Field

Assign values to static fields using the static `set` method of the class. Alternatively, assign values using an instance of the class. For more information, see “Accessing Data from a Static Field” on page 10-20. You can assign `value` to the field `staticFieldName` in the following example by referring to this field as an instance of the class.

```
objectName = java.className;  
objectName.staticFieldName = value;
```

---

**Note:** MATLAB does not allow assignment to static fields using the class name itself.

---

### Determining the Class of an Object

To find the class of a Java object, use the query form of the `class` function. After execution of the following example, `myClass` contains the name of the package and class that the object `value` instantiates.

```
value = java.lang.Integer(0);  
myClass = class(value)
```

```
myClass =  
java.lang.Integer
```

Because this form of `class` also works on MATLAB objects, it does not, in itself, tell you whether it is a Java class. To determine the type of class, use the `isjava` function, which returns 1 if `obj` is a Java object, and 0 if it is not. For example, type:

```
isjava(value)
```

```
ans =  
    1
```

To find out if an object is an instance of a specified class, use the `isa` function. The class can be a MATLAB built-in or user-defined class, as well as a Java class. For example, type:

```
isa(value, 'java.lang.Integer')
```

```
ans =  
    1
```

# Java Object Methods

**In this section...**

“Calling Syntax” on page 10-23

“Obtaining Method Information” on page 10-25

“Java Methods That Affect MATLAB Commands” on page 10-28

“How MATLAB Handles Undefined Methods” on page 10-29

“Handling Java Exceptions” on page 10-30

“Method Execution in MATLAB” on page 10-30

## Calling Syntax

To call methods on Java objects, you can use either Java calling syntax or MATLAB calling syntax. Under certain circumstances, use the MATLAB `javaMethod` function.

- “Java Calling Syntax” on page 10-23
- “MATLAB Calling Syntax” on page 10-23
- “Using the `javaMethod` Function” on page 10-24
- “Calling Syntax for Static Methods of Java Classes” on page 10-24

### Java Calling Syntax

To call methods on Java objects, use the Java syntax:

```
object.method(arg1, ..., argn)
```

### MATLAB Calling Syntax

To call methods on Java objects, use the MATLAB syntax:

```
method(object, arg1, ..., argn)
```

For example, to call the `getHours` and `setHours` methods using MATLAB syntax:

```
m1Date = java.util.Date;  
setHours(m1Date, 3)  
getHours(m1Date)
```

```
ans =
```

## Using the `javaMethod` Function

---

**Note:** The MATLAB syntax is the preferred syntax for invoking a Java method. Use `javaMethod` for these special cases only.

---

Use the MATLAB `javaMethod` function to:

- Use Java methods with names that exceed the maximum length of a MATLAB identifier. (Call the `namelengthmax` function to obtain the maximum identifier length.)
- Specify a Java method to invoke at run time.

For example, your code calls `javaMethod` with a character vector variable in place of the `method` argument. When you use `javaMethod` to invoke a static method, you also can use a character vector variable in place of the class name argument.

- Call the constructor of or a static method in an inner class. In the `javaMethod` and `javaObject` functions, specify the class name, using the `$` character, as `OuterClass$InnerClass`.

For example, suppose class `com.ams.MyClass` contains class `MyInnerClass` with static method `methodName`. In Java, the calling syntax is:

```
out = com.ams.MyClass.MyInnerClass.methodName(arg);
```

In MATLAB, type:

```
out = javaMethod('methodName', 'com.ams.MyClass$MyInnerClass', arg)
```

### Calling Syntax for Static Methods of Java Classes

To invoke a static method on a Java class, use the Java syntax:

```
class.method(arg1, ..., argn)
```

For example, call the static method, `isNaN`:

```
java.lang.Double.isNaN(2.2)
```

```
ans =  
    0
```



## Obtaining Method Information

MATLAB provides the `methods` and `methodsview` functions to obtain information about the Java methods you are using. You also can request a listing of every Java class that you loaded into MATLAB that implements a specified method.

- “Using methods to Display Method Names and Arguments” on page 10-25
- “Using `methodsview` to Display Argument Types and Exceptions” on page 10-26
- “Using `which` to Determine What Classes Define a Method” on page 10-27

### Using `methods` to Display Method Names and Arguments

The `methods` function returns information on methods of MATLAB and Java classes.

To return the names of all the methods (including inherited methods) of the class, use `methods` without the `'-full'` qualifier. Names of overloaded methods are listed only once.

With the `'-full'` qualifier, `methods` returns a listing of the method names (including inherited methods) along with attributes, argument lists, and inheritance information on each. Each overloaded method is listed separately.

For example, display a full description of all methods of the `java.awt.Dimension` object.

```
methods java.awt.Dimension -full
```

```
Methods for class java.awt.Dimension:
Dimension()
Dimension(java.awt.Dimension)
Dimension(int,int)
java.lang.Class getClass() % Inherited from java.lang.Object
int hashCode() % Inherited from java.lang.Object
boolean equals(java.lang.Object)
java.lang.String toString()
void notify() % Inherited from java.lang.Object
void notifyAll() % Inherited from java.lang.Object
void wait(long) throws java.lang.InterruptedException
    % Inherited from java.lang.Object
void wait(long,int) throws java.lang.InterruptedException
    % Inherited from java.lang.Object
void wait() throws java.lang.InterruptedException
    % Inherited from java.lang.Object
```

```
java.awt.Dimension getSize()
void setSize(java.awt.Dimension)
void setSize(int,int)
```


### Using `methodsview` to Display Argument Types and Exceptions

To see methods implemented by a particular Java (or MATLAB) class, use the `methodsview` function. Specify the class name (along with its package name, for Java classes) in the command line. If you have imported the package that defines this class, then the class name alone suffices.

The following command lists information on all methods in the `java.awt.MenuItem` class. Type:

```
methodsview java.awt.MenuItem
```

A new window appears, listing one row of information for each method in the class.



Qualifiers	Return Type	Name	Arguments
		MenuItem	()
		MenuItem	(java.lang.String)
		MenuItem	(java.lang.String,java.awt.MenuShortcut)
synchronized	void	addActionListener	(java.awt.event.ActionListener)
	void	addNotify	()
	void	deleteShortcut	()
synchronized	void	disable	()
	void	dispatchEvent	(java.awt.AWTEvent)
synchronized	void	enable	()
	void	enable	(boolean)
	boolean	equals	(java.lang.Object)
	java.lang.String	getActionCommand	()
	java.lang.Class	getClass	()
	java.awt.Font	getFont	()
	java.lang.String	getLabel	()
	java.lang.String	getName	()
	java.awt.MenuContainer	getParent	()
	java.awt.peer.MenuComponentPeer	getPeer	()
	java.awt.MenuShortcut	getShortcut	()
	int	hashCode	()
	boolean	isEnabled	()
	void	notify	()
	void	notifyAll	()

Each row in the window displays up to six fields of information describing the method. The following table lists the fields displayed in the `methodsviw` window along with a description and examples of each field type.

### Fields Displayed in `methodsviw` Window

Field Name	Description	Examples
Qualifiers	Method type qualifiers	abstract, synchronized
Return Type	Type returned by the method	void, java.lang.String
Name	Method name	addActionListener, dispatchEvent
Arguments	Types of arguments passed to method	boolean, java.lang.Object
Other	Other relevant information	throws java.io.IOException
Inherited From	Parent of the specified class	java.awt.MenuComponent

### Using `which` to Determine What Classes Define a Method

Use the `which` function to display the fully qualified name (package and class name) of a method implemented by a *loaded* Java class. To find all classes that define the specified method, use the `which` function with the `-all` qualifier.

For example, suppose you want to find the package and class name for the `concat` method. Type:

```
which concat
```

If the `java.lang.String` class is loaded, MATLAB displays:

```
concat is a Java method % java.lang.String method
```

If the `String` class has not been loaded, MATLAB displays:

```
concat not found.
```

Suppose that you loaded the Java `String` and `java.awt.Frame` classes. Both of these classes have an `equals` method. Type:

```
which -all equals
```

The MATLAB display includes entries like the following:

```
equals is a Java method      % java.lang.String method
equals is a Java method      % java.awt.Frame.equals
equals is a Java method      % com.mathworks.jmi.MatlabPath method
```

The `which` function operates differently on Java classes than it does on MATLAB classes. `which` always displays MATLAB classes, whether they are loaded. `which` only displays Java classes that are loaded. You can find out which Java classes are currently loaded by using the command `[m,x,j]=inmem`, described in “Determining Which Classes Are Loaded” on page 10-9.

For a description of how Java classes are loaded, see “Making Java Classes Available in MATLAB Workspace” on page 10-7.

## Java Methods That Affect MATLAB Commands

MATLAB commands that operate on Java objects and arrays use the methods that are implemented within, or inherited by, these objects' classes. There are some MATLAB commands that you can alter in behavior by changing the Java methods that they use.

### Changing the Effect of `disp` and `display`

You are calling the `disp` function when you:

- Display the value of a variable or an expression in MATLAB.
- Terminate a command line without a semicolon.
- Display a Java object in MATLAB.

When calling `disp` on a Java object, MATLAB formats the output using the object `toString` method. If the class does not implement this method, then MATLAB uses an inherited `toString` method. If no intermediate ancestor classes define this method, MATLAB uses the `toString` method defined by the `java.lang.Object` class.

To change the way MATLAB displays an object, implement your own `toString` method in your class definition.

### Changing the Effect of `isequal`

The MATLAB `isequal` function compares two or more arrays for equality in type, size, and contents. Also, you can use this function to test Java objects for equality.

When you compare two Java objects using `isequal`, MATLAB performs the comparison using the Java method, `equals`. MATLAB first determines the class of the objects specified in the command, and then uses the `equals` method implemented by that class. If `equals` is not implemented in this class, then MATLAB uses an inherited `equals` method. If no intermediate ancestor classes define this method, MATLAB uses the `equals` method defined by the `java.lang.Object` class.

To change the way MATLAB compares members of a class, implement your own `equals` method in your class definition.

### Changing the Effect of `double` and `char`

You can change the output of the MATLAB `double` and `char` functions by defining your own Java methods, `toDouble` and `toChar`. For more information, see “Converting to the MATLAB double Type” on page 10-78 and “Converting to the MATLAB char Type” on page 10-79.

## How MATLAB Handles Undefined Methods

If your MATLAB command invokes a nonexistent method on a Java object, MATLAB looks for a function with the same name. If MATLAB finds a function of that name, it attempts to invoke it. If MATLAB does not find a function with that name, it displays a message stating that it cannot find a method by that name for the class.

For example, MATLAB has a function named `size`, and the Java API `java.awt.Frame` class also has a `size` method. If you call `size` on a `Frame` object, the `size` method defined by `java.awt.Frame` is executed. However, if you call `size` on an object of `java.lang.String`, MATLAB does not find a `size` method for this class. It executes the MATLAB `size` function instead.

```
text = java.lang.String('hello');  
size(text)
```

```
ans =  
    1     1
```

---

**Note:** When you define a Java class for use in MATLAB, avoid giving any of its methods the same name as a MATLAB function.

---

## Handling Java Exceptions

Use the `matlab.exception.JavaException` class to handle Java exceptions.

## Method Execution in MATLAB

When calling a `main` method from MATLAB, the method returns when it executes its last statement, even if the method creates a thread that is still executing. In other environments, the `main` method does not return until the thread completes execution.

You, therefore, be cautious when calling `main` methods from MATLAB, particularly `main` methods that start a user interface. `main` methods are written assuming they are the entry point to application code. When called from MATLAB this is not the case, and the fact that other Java UI code might be already running can lead to problems.

## Java Arrays

### In this section...

“Introduction” on page 10-31

“How MATLAB Represents the Java Array” on page 10-31

“Creating an Array of Objects in MATLAB” on page 10-35

“Accessing Elements of a Java Array” on page 10-38

“Assigning to a Java Array” on page 10-41

“Concatenating Java Arrays” on page 10-44

“Creating a New Array Reference” on page 10-45

“Creating a Copy of a Java Array” on page 10-46

### Introduction

You can pass singular Java objects to and from methods or you can pass them in an array, providing the method expects them in that form. This array must either be a Java array (returned from another method call or created within the MATLAB) or, under certain circumstances, a MATLAB cell array. This section describes how to create and manipulate Java arrays in MATLAB. Later sections describe how to use MATLAB cell arrays in calls to Java methods.

---

**Note:** The term *dimension* refers to the number of subscripts required to address the elements of an array. Dimension is not a measure of length, width, and height. For example, a 5-by-1 array is one-dimensional, as its individual elements can be indexed using one subscript.

---

### How MATLAB Represents the Java Array

The term *Java array* refers to any array of Java objects returned from a call to a Java class constructor or method. You can also construct a Java array within MATLAB using the `javaArray` function. The structure of a Java array is different from the structure of a MATLAB matrix or array. MATLAB *hides* these differences whenever possible, allowing you to operate on the arrays using the usual MATLAB command syntax. Just the same, keep in mind the following differences as you work with Java arrays.

- “Representing More Than One Dimension” on page 10-32
- “Array Indexing” on page 10-33
- “The Shape of the Java Array” on page 10-34
- “Interpreting the Size of a Java Array” on page 10-34
- “Interpreting the Number of Dimensions of a Java Arrays” on page 10-35


### **Representing More Than One Dimension**

An array in the Java language is strictly a one-dimensional structure because it is measured only in length. If you want to work with a two-dimensional array, you can create an equivalent structure using an array of arrays. To add further dimensions, you add more levels to the array, making it an array of arrays of arrays, and so on. You can use such multilevel arrays when working in MATLAB, as it is a matrix and array-based programming language.


MATLAB makes it easy for you to work with multilevel Java arrays by treating them like the matrices and multidimensional arrays that are a part of the language itself. You access elements of an array of arrays using the same MATLAB syntax that you use if you are handling a matrix. If you add more levels to the array, MATLAB can access and operate on the structure as if it is a multidimensional MATLAB array.

The left side of the following figure shows Java arrays of one, two, and three dimensions. To the right of each representation is the same array represented in MATLAB. Single-dimension arrays are represented as column vectors.




Array Access from Java


Simple Array

Array Access from MATLAB


One-dimensional Array




Array of Arrays



Two-Dimensional Array



Array of Arrays of Arrays



Three-Dimensional Array


**Array Indexing**

Java array indexing is different than MATLAB array indexing. Java array indices are zero-based, MATLAB array indices are one-based. In Java programming, you access the elements of array  $y$  of length  $N$  using  $y[0]$  through  $y[N-1]$ . When working with this array in MATLAB, you access these same elements using the MATLAB indexing style of  $y(1)$  through  $y(N)$ . Thus, if you have a Java array of 10 elements, the seventh element is obtained using  $y(7)$ , and not  $y[6]$  as you use when writing a Java language program.

### The Shape of the Java Array

A Java array can be different from a MATLAB array in its overall *shape*. A two-dimensional MATLAB array maintains a rectangular shape, as each row is of equal length and each column of equal height. The Java counterpart, an array of arrays, does not necessarily hold to this rectangular form. Each individual lower level array might have a different length.

The following picture shows an array of three underlying arrays of different lengths. The terms *jagged* or *ragged* are commonly used to describe this arrangement of array elements as the array ends do not match up evenly. When a Java method returns an array with this type of structure, it is stored in a cell array by MATLAB.




### Interpreting the Size of a Java Array

Calling the MATLAB `size` function on a Java array returns the length of the Java array. The number of columns is always 1.

Determining the size of a Java array of arrays is not so simple. The potentially ragged shape of an array returned from a Java method makes it impossible to size the array in the same way as for a rectangular matrix. In a ragged Java array, there is no single value that represents the size of the lower-level arrays.

When the `size` function is applied to a Java array of arrays, the resulting value describes the top level of the specified array. For the Java array:



`size(A)` returns the dimensions of the highest array level of `A`. The highest level of the array has a size of 3-by-1.

```
size(A)
ans =
     3     1
```

To find the size of a lower-level array, say the five-element array in row 3, refer to the row explicitly.

```
size(A(3))
ans =
     5     1
```

You can specify a dimension in the `size` command using the following syntax. However, this is useful only for sizing the first dimension, `dim=1`, the only non-unary dimension.

```
m = size(X,dim)
size(A, 1)
ans =
     3
```

### Interpreting the Number of Dimensions of a Java Arrays

The MATLAB `ndims` function always returns a value of 2 for the number of dimensions in a Java array. This is the number of dimensions in the top-level array.

## Creating an Array of Objects in MATLAB

To call a Java method that has one or more arguments defined as an array of Java objects, you must, under most circumstances, pass your objects in a Java array. You can construct an array of objects in a call to a Java method or constructor. Or you can create the array within MATLAB.

The MATLAB `javaArray` function lets you create a Java array structure that can be handled in MATLAB as a single multidimensional array. You specify the number and size of the array dimensions along with the class of objects you intend to store in it. Using the one-dimensional Java array as its primary building block, MATLAB then builds an array structure that satisfies the dimensions requested in the `javaArray` command.

- “Using the `javaArray` Function” on page 10-36
- “Using MATLAB Syntax” on page 10-36

### Using the `javaArray` Function

To create a Java object array, use the MATLAB `javaArray` function, which has the following syntax:

```
A = javaArray('element_class', m, n, p, ...)
```

The first argument is `'element_class'`, which names the class of the elements in the array. Specify the fully qualified name (package and class name). The remaining arguments (`m`, `n`, `p`, ...) are the number of elements in each dimension of the array.

An array that you create with `javaArray` is equivalent to the array that you create with the Java code.

```
A = new element_class[m][n][p]...;
```

The following command builds a Java array of four lower-level arrays, each capable of holding five objects of the `java.lang.Double` class.

```
dblArray = javaArray('java.lang.Double',4,5);
```

The `javaArray` function does not deposit any values into the array elements that it creates. You must do this separately. The following MATLAB code stores objects of the `java.lang.Double` type in the Java array `dblArray` that was created.

```
for m = 1:4
    for n = 1:5
        dblArray(m,n) = java.lang.Double((m*10) + n);
    end
end
```

```
dblArray
```

```
dblArray =
java.lang.Double[][]:
    [11]    [12]    [13]    [14]    [15]
    [21]    [22]    [23]    [24]    [25]
    [31]    [32]    [33]    [34]    [35]
    [41]    [42]    [43]    [44]    [45]
```

### Using MATLAB Syntax

You also can create an array of Java objects using syntax that is more typical to MATLAB. For example, the following syntax creates a 4-by-5 MATLAB array of type `double` and assigns zero to each element of the array.

```
matlabArr(4,5) = 0;
```

You use similar syntax to create a Java array in MATLAB, except that you specify the Java class name. The value being assigned, 0 in this example, is stored in the final element of the array, `javaArr(4,5)`. All other elements of the array receive the empty matrix.

```
javaArr(4,5) = java.lang.Double(0)
```

```
javaArr =
java.lang.Double[][]:
    []    []    []    []    []
    []    []    []    []    []
    []    []    []    []    []
    []    []    []    []    [0]
```

---

**Note:** You cannot change the number of dimensions of an existing Java array as you can with a MATLAB array. The same restriction exists when working with Java arrays in the Java language. See the following example.

---

This example first creates a scalar MATLAB array, and then changes it to a 2D array.

```
matlabArr = 0;
matlabArr(4,5) = 0
```

```
matlabArr =
    0    0    0    0    0
    0    0    0    0    0
    0    0    0    0    0
    0    0    0    0    0
```

When you try this technique with a Java array, you get an error message.

```
javaArr = java.lang.Double(0);
javaArr(4,5) = java.lang.Double(0);
```

```
Index exceeds Java array dimensions.
```

Similarly, you cannot create an array of Java arrays from a Java array.

## Accessing Elements of a Java Array

- “MATLAB Array Indexing” on page 10-38
- “Single Subscript Indexing” on page 10-38
- “Colon Operator Indexing” on page 10-39
- “Using END in a Subscript” on page 10-40
- “Elements of `java.lang.Object` Arrays Are Converted to MATLAB Types” on page 10-41

### MATLAB Array Indexing

You can access elements of a Java object array by using the MATLAB array indexing syntax, `A(row,col)`. For example, to access the element of array `dblArray` at row 3, column 4, use:

```
row3_col4 = dblArray(3,4)
```

```
row3_col4 =  
34.0
```

To access this element in a Java language program, use `dblArray[2][3]`.

You also can use MATLAB array indexing syntax to access an element in the data field of an object. Suppose that `myMenuObj` is an instance of a window menu class. This user-supplied class has a data field, `menuItemArray`, which is a Java array of `java.awt.MenuItem`. To get element 3 of this array, use the following command.

```
currentItem = myMenuObj.menuItemArray(3)
```

### Single Subscript Indexing

Elements of a MATLAB matrix are most commonly referenced using both row and column subscripts. For example, you use `x(3,4)` to reference the array element at the intersection of row 3 and column 4. Sometimes it is more advantageous to use just a single subscript. MATLAB provides this capability (see the section on “Linear Indexing” in MATLAB Mathematics).

Indexing into a MATLAB matrix using a single subscript references one element of the matrix. Using the MATLAB matrix shown here, `matlabArr(3)` returns a single element of the matrix.

```
matlabArr = [11 12 13 14 15; 21 22 23 24 25; ...
```

```

        31 32 33 34 35; 41 42 43 44 45]

matlabArr =
    11    12    13    14    15
    21    22    23    24    25
    31    32    33    34    35
    41    42    43    44    45

matlabArr(3)

ans =
    31

```

Indexing this way into a Java array of arrays references an entire subarray of the overall structure. Using the `dblArray` Java array, that looks the same as `matlabArr`, `dblArray(3)` returns the 5-by-1 array that makes up the entire third row.

```

row3 = dblArray(3)

row3 =
java.lang.Double[]:
 [31]
 [32]
 [33]
 [34]
 [35]

```

This feature allows you to specify an entire array from a larger array structure, and then manipulate it as an object.

### Colon Operator Indexing

Use of the MATLAB colon operator (`:`) is supported in subscripting Java array references. This operator works just the same as when referencing the contents of a MATLAB array. Using the Java array of `java.lang.Double` objects shown here, the statement `dblArray(2,2:4)` refers to a portion of the lower-level array, `dblArray(2)`. A new array, `row2Array`, is created from the elements in columns 2 through 4.

```

dblArray

dblArray =
java.lang.Double[][]:
 [11] [12] [13] [14] [15]
 [21] [22] [23] [24] [25]
 [31] [32] [33] [34] [35]
 [41] [42] [43] [44] [45]

```

```
row2Array = dblArray(2,2:4)

row2Array =
java.lang.Double[]:
    [22]
    [23]
    [24]
```

You also can use the colon operator in single-subscript indexing, as covered in “Single Subscript Indexing” on page 10-38. By making your subscript a colon rather than a number, you can convert an array of arrays into one linear array. The following example converts the 4-by-5 array `dblArray` into a 20-by-1 linear array.

```
linearArray = dblArray(:)

linearArray =
java.lang.Double[]:
    [11]
    [12]
    [13]
    [14]
    [15]
    [21]
    [22]
    .
    .
    .
```

This method also works on an N-dimensional Java array structure. Using the colon operator as a single subscripted index into the array produces a linear array composed of all of the elements of the original array.

---

**Note:** Java and MATLAB arrays are stored differently in memory. This is reflected in the order they are given in a linear array. Java array elements are stored in an order that matches the *rows* of the matrix (`linearArray` elements 11, 12, 13, ...). MATLAB array elements are stored in an order that matches the *columns* (elements 11, 21, 31, ...).

---

### Using END in a Subscript

You can use the `end` keyword in the first subscript of an access statement. The first subscript references the top-level array in a multilevel Java array structure.



---

**Note:** Using `end` on lower-level arrays is not valid due to the potentially ragged nature of these arrays (see “The Shape of the Java Array” on page 10-34). In this case, there is no consistent end value to be derived.

---

The following example displays data from the third to the last row of Java array `dblArray`.

```
last2rows = dblArray(3:end, :)

last2rows =
java.lang.Double[][]:
    [31]    [32]    [33]    [34]    [35]
    [41]    [42]    [43]    [44]    [45]
```

### Elements of `java.lang.Object` Arrays Are Converted to MATLAB Types

When you access an element of a `java.lang.Object` array, MATLAB converts the element to a MATLAB type, according to the table in “Conversion of Java Object Return Types” on page 10-77. MATLAB does not convert elements of any other type of Java array.

For example, if a `java.lang.Object` array contains a `java.lang.Double` element, MATLAB converts the element to MATLAB `double`. But MATLAB does not convert a `java.lang.Double` element in a `java.lang.Double` array; MATLAB returns it as `java.lang.Double`.

## Assigning to a Java Array

- “Using Single Subscript Indexing for Array Assignment” on page 10-42
- “Assigning to a Linear Array” on page 10-42
- “Assigning the Empty Matrix” on page 10-43
- “Subscripted Deletion” on page 10-43

You assign values to objects in a Java array in essentially the same way as you do in a MATLAB array. Although Java and MATLAB arrays are structured differently, you use the same command syntax to specify which elements you want to assign to. See “Introduction” on page 10-31 for more information on Java and MATLAB array differences.

The following example assigns the value 300 in the `dblArray` element at row 3, column 2. In a Java language program, this is `dblArray[2][1]`.

```
dblArray(3,2) = java.lang.Double(300)
```

```
dblArray =  
java.lang.Double[][]:  
    [11]    [ 12]    [13]    [14]    [15]  
    [21]    [ 22]    [23]    [24]    [25]  
    [31]    [300]    [33]    [34]    [35]  
    [41]    [ 42]    [43]    [44]    [45]
```

Use the same syntax to assign to an element to the data field of an object. Continuing with the `myMenuObj` example shown in “Accessing Elements of a Java Array” on page 10-38, assign to the third menu item in `menuItemArray` as follows.

```
myMenuObj.menuItemArray(3) = java.lang.String('Save As...');
```

### Using Single Subscript Indexing for Array Assignment

You can use a single-array subscript to index into a Java array structure that has more than one dimension. Refer to “Single Subscript Indexing” on page 10-38 for a description of this feature as used with Java arrays.

You can use single-subscript indexing to assign values to an array as well. The following example assigns a one-dimensional Java array, `onedimArray`, to a row of a two-dimensional Java array, `dblArray`. Start out by creating the one-dimensional array.

```
onedimArray = javaArray('java.lang.Double', 5);  
for k = 1:5  
    onedimArray(k) = java.lang.Double(100 * k);  
end
```

Since `dblArray(3)` refers to the 5-by-1 array displayed in the third row of `dblArray`, you can assign the entire, similarly dimensioned, 5-by-1 `onedimArray` to it.

```
dblArray(3) = onedimArray
```

```
dblArray =  
java.lang.Double[][]:  
    [ 11]    [ 12]    [ 13]    [ 14]    [ 15]  
    [ 21]    [ 22]    [ 23]    [ 24]    [ 25]  
    [100]    [200]    [300]    [400]    [500]  
    [ 41]    [ 42]    [ 43]    [ 44]    [ 45]
```

### Assigning to a Linear Array

You can assign a value to *every* element of a multidimensional Java array by treating the array structure as if it were a single linear array. This entails replacing the single,

numerical subscript with the MATLAB colon operator. If you start with the `dblArray` array, you can initialize the contents of every object in the two-dimensional array with the following statement.

```
dblArray(:) = java.lang.Double(0)
```

```
dblArray =
java.lang.Double[][]:
    [0]    [0]    [0]    [0]    [0]
    [0]    [0]    [0]    [0]    [0]
    [0]    [0]    [0]    [0]    [0]
    [0]    [0]    [0]    [0]    [0]
```

You can use the MATLAB colon operator as you would when working with MATLAB arrays. The following statements assign given values to each of the four rows in the Java array, `dblArray`. Remember that each row actually represents a separate Java array in itself.

```
dblArray(1,:) = java.lang.Double(125);
dblArray(2,:) = java.lang.Double(250);
dblArray(3,:) = java.lang.Double(375);
dblArray(4,:) = java.lang.Double(500)
```

```
dblArray =
java.lang.Double[][]:
    [125]    [125]    [125]    [125]    [125]
    [250]    [250]    [250]    [250]    [250]
    [375]    [375]    [375]    [375]    [375]
    [500]    [500]    [500]    [500]    [500]
```

### Assigning the Empty Matrix

When working with MATLAB arrays, you can assign the empty matrix, (that is, the 0-by-0 array denoted by `[]`) to an element of the array. For Java arrays, you also can assign `[]` to array elements. This stores the `null` value, rather than a 0-by-0 array, in the Java array element.

### Subscripted Deletion

When you assign the empty matrix value to an entire row or column of a MATLAB array, you find that MATLAB actually removes the affected row or column from the array. In the example below, the empty matrix is assigned to all elements of the fourth column in the MATLAB matrix, `matlabArr`. Thus, the fourth column is eliminated from the matrix. This changes its dimensions from 4-by-5 to 4-by-4.

```
matlabArr = [11 12 13 14 15; 21 22 23 24 25; ...  
            31 32 33 34 35; 41 42 43 44 45]
```

```
matlabArr =  
    11    12    13    14    15  
    21    22    23    24    25  
    31    32    33    34    35  
    41    42    43    44    45
```

```
matlabArr(:,4) = []
```

```
matlabArr =  
    11    12    13    15  
    21    22    23    25  
    31    32    33    35  
    41    42    43    45
```

You can assign the empty matrix to a Java array, but the effect is different. The next example shows that, when the same operation is performed on a Java array, the structure is not collapsed; it maintains its 4-by-5 dimensions.

```
dblArray(:,4) = []
```

```
dblArray =  
java.lang.Double[][]:  
    [125]    [125]    [125]    []    [125]  
    [250]    [250]    [250]    []    [250]  
    [375]    [375]    [375]    []    [375]  
    [500]    [500]    [500]    []    [500]
```

The `dblArray` data structure is actually an array of five-element arrays of `java.lang.Double` objects. The empty array assignment placed the `null` value in the fourth element of each of the lower-level arrays.

## Concatenating Java Arrays

You can concatenate arrays of Java objects in the same way as arrays of other types. Java objects, however, can only be concatenated along the first or second axis. To understand how scalar Java objects are concatenated in MATLAB, see “Concatenating Java Objects” on page 10-17.

Use either the `cat` function or the square bracket (`[]`) operators. This example horizontally concatenates two Java arrays: `d1` and `d2`.

```
% Construct a 2-by-3 array of java.lang.Double.
d1 = javaArray('java.lang.Double',2,3);
for m = 1:2
    for n = 1:3
        d1(m,n) = java.lang.Double(n*2 + m-1);
    end
end

d1

d1 =
java.lang.Double[][]:
    [2]    [4]    [6]
    [3]    [5]    [7]

% Construct a 2-by-2 array of java.lang.Double.
d2 = javaArray('java.lang.Double',2,2);
for m = 1:2
    for n = 1:2
        d2(m,n) = java.lang.Double((n+3)*2 + m-1);
    end
end

d2

d2 =
java.lang.Double[][]:
    [8]    [10]
    [9]    [11]

% Concatenate the two along the second dimension.
d3 = cat(2,d1,d2)

d3 =
java.lang.Double[][]:
    [2]    [4]    [6]    [ 8]    [10]
    [3]    [5]    [7]    [ 9]    [11]
```

## Creating a New Array Reference

Because Java arrays in MATLAB are *references*, assigning an array variable to another variable results in a second reference to the array.

Consider the following example where two separate array variables reference a common array. The original array, `origArray`, is created and initialized. The statement

`newArrayRef = origArray` creates a copy of this array variable. Changes made to the array referred to by `newArrayRef` also show up in the original array.

```
origArray = javaArray('java.lang.Double', 3, 4);
for m = 1:3
    for n = 1:4
        origArray(m,n) = java.lang.Double((m * 10) + n);
    end
end
```

`origArray`

```
origArray =
java.lang.Double[][]:
    [11]    [12]    [13]    [14]
    [21]    [22]    [23]    [24]
    [31]    [32]    [33]    [34]
```

`% Make a copy of the array reference`

```
newArrayRef = origArray;
newArrayRef(3,:) = java.lang.Double(0);
```

`origArray`

```
origArray =
java.lang.Double[][]:
    [11]    [12]    [13]    [14]
    [21]    [22]    [23]    [24]
    [ 0]    [ 0]    [ 0]    [ 0]
```

## Creating a Copy of a Java Array

You can create an entirely new array from an existing Java array by indexing into the array to describe a block of elements, or subarray, and assigning this subarray to a variable. The assignment copies the values in the original array to the corresponding cells of the new array.

As with the example in section “Creating a New Array Reference” on page 10-45, an original array is created and initialized. But, this time, a copy is made of the array contents rather than copying the array reference. Changes made using the reference to the new array do not affect the original.

```
origArray = javaArray('java.lang.Double', 3, 4);
for m = 1:3
```

```
    for n = 1:4
        origArray(m,n) = java.lang.Double((m * 10) + n);
    end
end
```

```
origArray
```

```
origArray =
java.lang.Double[][]:
    [11]    [12]    [13]    [14]
    [21]    [22]    [23]    [24]
    [31]    [32]    [33]    [34]
```

```
% ----- Make a copy of the array contents -----
newArray = origArray(:,:);
newArray(3,:) = java.lang.Double(0);
```

```
origArray
```

```
origArray =
java.lang.Double[][]:
    [11]    [12]    [13]    [14]
    [21]    [22]    [23]    [24]
    [31]    [32]    [33]    [34]
```

## Read URL Using `java.net.URL`

In this section...
“Overview” on page 10-48
“Description of URLdemo” on page 10-48
“Running the Example” on page 10-49

### Overview

This program, `URLdemo`, opens a connection to a website specified by a URL (Uniform Resource Locator) to read text from a file at that site. For examples accessing website content using MATLAB functions, see “Web Access”.

`URLdemo` constructs an object of the Java API class, `java.net.URL`, which enables convenient handling of URLs. Then, it calls a method on the URL object, to open a connection.

To read and display the lines of text at the site, `URLdemo` uses classes from the Java I/O package `java.io`. It creates an `InputStreamReader` object, and then uses that object to construct a `BufferedReader` object. Finally, it calls a method on the `BufferedReader` object to read the specified number of lines from the site.

### Description of URLdemo

The major tasks performed by `URLdemo` are:

- 1 Construct a URL object.

The example first calls a constructor on `java.net.URL` and assigns the resulting object to variable `url`. The URL constructor takes a single argument, the name of the URL to be accessed. The constructor checks whether the input URL has a valid form.

```
url = java.net.URL('http://www.mathworks.com')
```

- 2 Open a connection to the URL.

The second statement of the example calls the method, `openStream`, on the URL object `url`, to establish a connection with the website named by the object. The method returns an `InputStream` object to variable, `is`, for reading bytes from the site.



```
is = openStream(url);
```

- 3 Set up a buffered stream reader.

The next two lines create a buffered stream reader for characters. The `java.io.InputStreamReader` constructor is called with the input stream `is`, to return to variable `isr` an object that can read characters. Then, the `java.io.BufferedReader` constructor is called with `isr`, to return a `BufferedReader` object to variable `br`. A buffered reader provides for efficient reading of characters, arrays, and lines.

```
isr = java.io.InputStreamReader(is);
br = java.io.BufferedReader(isr);
```

- 4 Read and display lines of text.

The following statements read the lines of HTML text from the site, looking for text beginning with a paragraph tag, `<p>`. Within the MATLAB `while` loop, the `BufferedReader` method `readLine` reads each line of text (terminated by a return and/or line feed character) from the site.

```
p1 = java.lang.String('<p>');
p2 = java.lang.String('</p>');
s = readLine(br);
while ~(s.startsWith(p1))
    s = readLine(br);
end
```

- 5 Display the text.

```
disp(s.substring(p1.length,s.length-p2.length))
```

## Running the Example

When you run this example, you see output similar to the following.

Explore products for MATLAB, the language of technical computing, and Simulink, for sin

## More About

- “Web Access”

## Find Internet Protocol Address Using `java.net.InetAddress`

### In this section...

“Overview” on page 10-50

“Description of `resolveip`” on page 10-50

“Run the Example” on page 10-51

### Overview

The `resolveip` function returns either the name or address of an IP (internet protocol) host. If you pass `resolveip` a host name, it returns the IP address. If you pass `resolveip` an IP address, it returns the host name. The function uses the `java.net.InetAddress` class, which enables you to find an IP address for a host name, or the host name for a given IP address, without making DNS calls.

`resolveip` calls a static method on the `InetAddress` class to obtain an `InetAddress` object. Then, it calls accessor methods on the `InetAddress` object to get the host name and IP address for the input argument. It displays either the host name or the IP address, depending on the program input argument.

### Description of `resolveip`

The major tasks performed by `resolveip` are:

- 1 Create an `InetAddress` object.

Instead of constructors, the `java.net.InetAddress` class has static methods that return an instance of the class. The `try` statement calls one of those methods, `getByName`, passing the input argument to `resolveip`. The input argument can be either a host name or an IP address. If `getByName` fails, the `catch` statement displays an `error` message.

```
function resolveip(input)
try
    address = java.net.InetAddress.getByName(input);
catch
    error(sprintf('Unknown host %s.', input))
end
```

## 2 Retrieve the host name and IP address.

The example uses calls to the `getHostName` and `getHostAddress` accessor functions on the `java.net.InetAddress` object, to obtain the host name and IP address, respectively. These two functions return objects of class `java.lang.String`; use the `char` function to convert them to character arrays.

```
hostname = char(address.getHostName);  
ipaddress = char(address.getHostAddress);
```

## 3 Display the host name or IP address.

The example uses the MATLAB `strcmp` function to compare the input argument to the resolved IP address. If it matches, MATLAB displays the host name for the internet address. If the input does not match, MATLAB displays the IP address.

```
if strcmp(input,ipaddress)  
    disp(sprintf('Host name of %s is %s', input, hostname))  
else  
    disp(sprintf('IP address of %s is %s', input, ipaddress))  
end
```

## Run the Example

Create the `resolveip` function.

```
function resolveip(input)  
try  
    address = java.net.InetAddress.getByName(input);  
catch  
    error(sprintf('Unknown host %s.', input))  
end  
hostname = char(address.getHostName);  
ipaddress = char(address.getHostAddress);  
if strcmp(input,ipaddress)  
    disp(sprintf('Host name of %s is %s', input, hostname));  
else  
    disp(sprintf('IP address of %s is %s', input, ipaddress));  
end;  
end
```

Call the function with a host name.

```
resolveip ('www.mathworks.com')
```

IP address of www.mathworks.com is 144.212.100.10

Call the function with an IP address.

```
resolveip ('144.212.100.10')
```

Host name of 144.212.100.10 is www.mathworks.com

## Create and Use Phone Book Using Java Classes

### In this section...

“Overview” on page 10-53

“Description of Function `phonebook`” on page 10-54

“Description of Function `pb_lookup`” on page 10-58

“Description of Function `pb_add`” on page 10-58

“Description of Function `pb_remove`” on page 10-59

“Description of Function `pb_change`” on page 10-60

“Description of Function `pb_listall`” on page 10-61

“Description of Function `pb_display`” on page 10-62

“Description of Function `pb_keyfilter`” on page 10-62

“Running the `phonebook` Program” on page 10-63

### Overview

The main function, `phonebook`, can be called either with no arguments, or with one argument, which is the key of an entry that exists in the phone book. The function first determines the folder to use for the phone book file.

If no phone book file exists, it creates one by constructing a `java.io.FileOutputStream` object, and then closing the output stream. Next, it creates a data dictionary by constructing an object of `java.util.Properties`, which is a subclass of `java.util.Hashtable`, for storing key/value pairs in a hash table. For the `phonebook` program, the key is a name, and the value is one or more telephone numbers.

The `phonebook` function creates and opens an input stream for reading by constructing a `java.io.FileInputStream` object. It calls `load` on that object to load the hash table contents, if it exists. If the user passed the key to an entry to look up, it looks up the entry by calling `pb_lookup`, which finds and displays it. Then, the `phonebook` function returns.

If `phonebook` was called without the name argument, it then displays a textual menu of the available phone book actions:

- Look up an entry
- Add an entry

- Remove an entry
- Change the phone number(s) in an entry
- List all entries

The menu also has a selection to exit the program. The function uses MATLAB functions to display the menu and to input the user selection.

The `phonebook` function iterates accepting user selections and performing the requested phone book action until the user selects the menu entry to exit. The `phonebook` function then opens an output stream for the file by constructing a `java.io.FileOutputStream` object. It calls `save` on the object to write the current data dictionary to the phone book file. It finally closes the output stream and returns.

## Description of Function `phonebook`

The major tasks performed by `phonebook` are:

- 1 Determine the data folder and full file name.

The first statement assigns the phone book file name, 'myphonebook', to the variable `pbname`. If the `phonebook` program is running on a Windows system, it calls the `java.lang.System` static method `getProperty` to find the location of the data dictionary. This is set to the user's current working folder. Otherwise, it uses MATLAB function `getenv` to determine the location, using the system variable `HOME`, which you can define beforehand to anything you like. It then assigns to `pbname` the full path, consisting of the data folder and file name 'myphonebook'.

```
function phonebook(varargin)
pbname = 'myphonebook'; % name of data dictionary
if ispc
    datadir = char(java.lang.System.getProperty('user.dir'));
else
    datadir = getenv('HOME');
end
pbname = fullfile(datadir, pbname);
```

- 2 If needed, create a file output stream.

If the `phonebook` file does not exist, `phonebook` asks the user whether to create a new one. If the user answers `y`, `phonebook` creates a phone book by constructing a `FileOutputStream` object. In the `try` clause of a `try/catch` block, the argument `pbname` passed to the `FileOutputStream` constructor is the full name of the file

that the constructor creates and opens. The next statement closes the file by calling `close` on the `FileOutputStream` object `FOS`. If the output stream constructor fails, the `catch` statement prints a message and terminates the program.

```

if ~exist(pbname)
  disp(sprintf('Data file %s does not exist.', pbname))
  r = input('Create a new phone book (y/n)?','s');
  if r == 'y',
    try
      FOS = java.io.FileOutputStream(pbname);
      FOS.close
    catch
      error(sprintf('Failed to create %s', pbname))
    end
  else
    return
  end
end
end

```

### 3 Create a hash table.

The example constructs a `java.util.Properties` object to serve as the hash table for the data dictionary.

```
pb_hhtable = java.util.Properties;
```

### 4 Create a file input stream.

In a `try` block, the example invokes a `FileInputStream` constructor with the name of the phone book file, assigning the object to `FIS`. If the call fails, the `catch` statement displays an `error` message and terminates the program.

```

try
  FIS = java.io.FileInputStream(pbname);
catch
  error(sprintf('Failed to open %s for reading.', pbname))
end

```

### 5 Load the phone book keys and close the file input stream.

The example calls `load` on the `FileInputStream` object `FIS`, to load the phone book keys and their values (if any) into the hash table. It then closes the file input stream.

```

pb_hhtable.load(FIS)
FIS.close

```

**6** Display the Action menu and get the user's selection.

Within a `while` loop, several `disp` statements display a menu of actions that the user can perform on the phone book. Then, an `input` statement requests the user's typed selection.

```
while 1
    disp ' '
    disp ' Phonebook Menu:'
    disp ' '
    disp ' 1. Look up a phone number'
    disp ' 2. Add an entry to the phone book'
    disp ' 3. Remove an entry from the phone book'
    disp ' 4. Change the contents of an entry in the phone book'
    disp ' 5. Display entire contents of the phone book'
    disp ' 6. Exit this program'
    disp ' '
    s = input('Please type the number for a menu selection: ','s');
```

**7** Invoke the function to perform a phone book action

Still within the `while` loop, a `switch` statement provides a case to handle each user selection `s`. Each of the first five cases invokes the function to perform a phone book action.

```
switch s
```

Case 1 prompts for a name that is a key to an entry. It calls `isempty` to determine whether the user has entered a name. If a name has not been entered, it calls `disp` to display an error message. If a name has been input, it passes it to `pb_lookup`. The `pb_lookup` routine looks up the entry and, if it finds it, displays the entry contents.

```
case '1',
    name = input('Enter name to look up: ','s');
    if isempty(name)
        disp 'No name entered'
    else
        pb_lookup(pb_htable, name)
    end
```

Case 2 calls `pb_add`, which prompts the user for a new entry and then adds it to the phone book.



```
case '2',
    pb_add(pb_hhtable)
```

Case 3 uses `input` to prompt for the name of an entry to remove. If a name has not been entered, it calls `disp` to display an error message. If a name has been entered, it passes it to `pb_remove`.

```
case '3',
    name = input('Enter name of entry to remove: ', 's');
    if isempty(name)
        disp 'No name entered'
    else
        pb_remove(pb_hhtable, name)
    end
```

Case 4 uses `input` to prompt for the name of an entry to change. If a name has not been entered, it calls `disp` to display an error message. If a name has been entered, it passes it to `pb_change`.

```
case '4',
    name = input('Enter name of entry to change: ', 's');
    if isempty(name)
        disp 'No name entered'
    else
        pb_change(pb_hhtable, name)
    end
```

Case 5 calls `pb_listall` to display all entries.

```
case '5',
    pb_listall(pb_hhtable)
```

## 8 Exit by creating an output stream and saving the phone book.

If the user has selected case 6 to exit the program, a `try` statement calls the constructor for a `FileOuputStream` object, passing it the name of the phone book. If the constructor fails, the `catch` statement displays an error message.

If the object is created, the next statement saves the phone book data by calling `save` on the `Properties` object `pb_hhtable`, passing the `FileOutputStream` object `FOS` and a descriptive header. It then calls `close` on the `FileOutputStream` object, and returns.

```
case '6',
    try
        FOS = java.io.FileOutputStream(pbname);
    catch
        error(sprintf('Failed to open %s for writing.',pbname))
    end
    pb_hhtable.save(FOS, 'Data file for phonebook program')
    FOS.close
    return
otherwise
    disp 'That selection is not on the menu.'
end

end % switch
```

## Description of Function `pb_lookup`

Arguments passed to `pb_lookup` are the Properties object `pb_hhtable` and the name key for the requested entry. The `pb_lookup` function first calls `get` on `pb_hhtable` with the name key, on which support function `pb_keyfilter` is called to change spaces to underscores. The `get` method returns the entry (or null, if the entry is not found) to variable `entry`. `get` takes an argument of type `java.lang.Object` and also returns an argument of that type. In this invocation, the key passed to `get` and the entry returned from it are actually character arrays.

`pb_lookup` then calls `isempty` to determine whether `entry` is null. If it is, it uses `disp` to display a message stating that the name was not found. If `entry` is not null, it calls `pb_display` to display the entry.

```
function pb_lookup(pb_hhtable,name)
entry = pb_hhtable.get(pb_keyfilter(name));
if isempty(entry),
    disp(sprintf('The name %s is not in the phone book',name))
else
    pb_display(entry)
end
```

## Description of Function `pb_add`

- 1 Input the entry to add.

The `pb_add` function takes one argument, the `Properties` object `pb_htable`. `pb_add` uses `disp` to prompt for an entry. Using the up arrow (^) character as a line delimiter, `input` inputs a name to the variable `entry`. Then, within a `while` loop, it uses `input` to get another line of the entry into variable `line`. If the line is empty, indicating that the user has finished the entry, the code breaks out of the `while` loop. If the line is not empty, the `else` statement appends line to `entry` and then appends the line delimiter. At the end, the `strcmp` checks the possibility that no input was entered and, if that is the case, returns.

```
function pb_add(pb_htable)
disp 'Type the name for the new entry, followed by Enter.'
disp 'Then, type the phone number(s), one per line.'
disp 'To complete the entry, type an extra Enter.'
name = input(':: ', 's');
entry = [name '^'];
while 1
    line = input(':: ', 's');
    if isempty(line)
        break
    else
        entry = [entry line '^'];
    end
end

if strcmp(entry, '^')
    disp 'No name entered'
    return
end
```

- 2 Add the entry to the phone book.

After the input has completed, `pb_add` calls `put` on `pb_htable` with the hash key name (on which `pb_keyfilter` is called to change spaces to underscores) and `entry`. It then displays a message that the entry has been added.

```
pb_htable.put(pb_keyfilter(name), entry)
disp ' '
disp(sprintf('%s has been added to the phone book.', name))
```

## Description of Function `pb_remove`

- 1 Look for the key in the phone book.

Arguments passed to `pb_remove` are the `Properties` object `pb_hhtable` and the name `key` for the entry to remove. The `pb_remove` function calls `containsKey` on `pb_hhtable` with the `name` key, on which support function `pb_keyfilter` is called to change spaces to underscores. If `name` is not in the phone book, `disp` displays a message and the function returns.

```
function pb_remove(pb_hhtable,name)
if ~pb_hhtable.containsKey(pb_keyfilter(name))
    disp(sprintf('The name %s is not in the phone book',name))
    return
end
```

- 2 Ask for confirmation and if given, remove the key.

If the key is in the hash table, `pb_remove` asks for user confirmation. If the user confirms the removal by entering `y`, `pb_remove` calls `remove` on `pb_hhtable` with the (filtered) `name` key, and displays a message that the entry has been removed. If the user enters `n`, the removal is not performed and `disp` displays a message that the removal has not been performed.

```
r = input(sprintf('Remove entry %s (y/n)? ',name), 's');
if r == 'y'
    pb_hhtable.remove(pb_keyfilter(name))
    disp(sprintf('%s has been removed from the phone book',name))
else
    disp(sprintf('%s has not been removed',name))
end
```

## Description of Function `pb_change`

- 1 Find the entry to change, and confirm.

Arguments passed to `pb_change` are the `Properties` object `pb_hhtable` and the name `key` for the requested entry. The `pb_change` function calls `get` on `pb_hhtable` with the `name` key, on which `pb_keyfilter` is called to change spaces to underscores. The `get` method returns the entry (or `null`, if the entry is not found) to variable `entry`. `pb_change` calls `isempty` to determine whether the entry is empty. If the entry is empty, `pb_change` displays a message that the name is added to the phone book, and allows the user to enter the phone number for the entry.

If the entry is found, in the `else` clause, `pb_change` calls `pb_display` to display the entry. It then uses `input` to ask the user to confirm the replacement. If the user enters anything other than `y`, the function returns.

```

function pb_change(pb_hhtable,name)
entry = pb_hhtable.get(pb_keyfilter(name));
if isempty(entry)
    disp(sprintf('The name %s is not in the phone book', name))
    return
else
    pb_display(entry)
    r = input('Replace phone numbers in this entry (y/n)? ','s');
    if r ~= 'y'
        return
    end
end
end

```

- 2 Input new phone numbers and change the phone book entry.

`pb_change` uses `disp` to display a prompt for new phone numbers. Then, `pb_change` inputs data into variable `entry`, with the same statements described in “Description of Function `pb_lookup`” on page 10-58.

Then, to replace the existing entry with the new one, `pb_change` calls `put` on `pb_hhtable` with the (filtered) key `name` and the new entry. It then displays a message that the entry has been changed.

```

disp 'Type in the new phone number(s), one per line.'
disp 'To complete the entry, type an extra Enter.'
disp(sprintf(':: %s', name))
entry = [name '^'];
while 1
    line = input(':: ','s');
    if isempty(line)
        break
    else
        entry = [entry line '^'];
    end
end
pb_hhtable.put(pb_keyfilter(name),entry)
disp ' '
disp(sprintf('The entry for %s has been changed', name))

```

## Description of Function `pb_listall`

The `pb_listall` function takes one argument, the `Properties` object `pb_hhtable`. The function calls `propertyNames` on the `pb_hhtable` object to return to `enum` a

`java.util.Enumeration` object, which supports convenient enumeration of all the keys. In a `while` loop, `pb_listall` calls `hasMoreElements` on `enum`, and if it returns true, `pb_listall` calls `nextElement` on `enum` to return the next key. It then calls `pb_display` to display the key and entry, which it retrieves by calling `get` on `pb_hhtable` with the key.

```
function pb_listall(pb_hhtable)
enum = pb_hhtable.propertyNames;
while enum.hasMoreElements
    key = enum.nextElement;
    pb_display(pb_hhtable.get(key))
end
```

## Description of Function `pb_display`

The `pb_display` function takes an argument `entry`, which is a phone book entry. After displaying a horizontal line, `pb_display` calls MATLAB function `strtok` to extract the first line of the entry, up to the line delimiter (^), into `t` and the remainder into `r`. Then, within a `while` loop that terminates when `t` is empty, it displays the current line in `t`. Then it calls `strtok` to extract the next line from `r`, into `t`. When all lines have been displayed, `pb_display` indicates the end of the entry by displaying another horizontal line.

```
function pb_display(entry)
disp ' '
disp '-----'
[t,r] = strtok(entry, '^');
while ~isempty(t)
    disp(sprintf(' %s',t))
    [t,r] = strtok(r, '^');
end
disp '-----'
```

## Description of Function `pb_keyfilter`

The `pb_keyfilter` function takes an argument `key`, which is a name used as a key in the hash table, and either filters it for storage or unfilters it for display. The filter, which replaces each space in the key with an underscore (`_`), makes the key usable with the methods of `java.util.Properties`.

```
function out = pb_keyfilter(key)
if ~isempty(strfind(key, ' '))
```

```

    out = strep(key, ' ', '_');
else
    out = strep(key, '_ ', ' ');
end

```

## Running the phonebook Program

In this sample run, a user invokes `phonebook` with no arguments. The user selects menu action 5, which displays the two entries currently in the phone book (all entries are fictitious). Then, the user selects 2, to add an entry. After adding the entry, the user again selects 5, which displays the new entry along with the other two entries.

Phonebook Menu:

1. Look up a phone number
2. Add an entry to the phone book
3. Remove an entry from the phone book
4. Change the contents of an entry in the phone book
5. Display entire contents of the phone book
6. Exit this program

Please type the number for a menu selection: 5

```

-----
Sylvia Woodland
(508) 111-3456
-----

```

```

-----
Russell Reddy
(617) 999-8765
-----

```

Phonebook Menu:

1. Look up a phone number
2. Add an entry to the phone book
3. Remove an entry from the phone book
4. Change the contents of an entry in the phone book
5. Display entire contents of the phone book
6. Exit this program

Please type the number for a menu selection: 2

Type the name for the new entry, followed by Enter.  
Then, type the phone number(s), one per line.  
To complete the entry, type an extra Enter.  
:: BriteLites Books  
:: (781) 777-6868  
::

BriteLites Books has been added to the phone book.

Phonebook Menu:

1. Look up a phone number
2. Add an entry to the phone book
3. Remove an entry from the phone book
4. Change the contents of an entry in the phone book
5. Display entire contents of the phone book
6. Exit this program

Please type the number for a menu selection: 5

```
-----  
BriteLites Books  
(781) 777-6868  
-----  
  
-----  
Sylvia Woodland  
(508) 111-3456  
-----  
  
-----  
Russell Reddy  
(617) 999-8765  
-----
```



## Java Heap Memory Preferences


You can adjust the amount of memory that MATLAB software allocates for Java objects.

---

**Note:** The default heap size is sufficient for most cases.

---

To adjust the Java heap size:

- 1 On the **Home** tab, in the **Environment** section, click  **Preferences**. Select **MATLAB > General > Java Heap Memory**.
- 2 Select a Java heap size value using the slider or spin box.

---

**Note:** Increasing the Java heap size decreases the amount of memory available for storing data in arrays.

---

- 3 Click **OK**.
- 4 Restart MATLAB.

If the amount of memory you specified is not available upon restart, MATLAB resets the value to the default, and displays an error dialog box. To readjust the value, repeat the previous steps.

If increasing the heap size does not eliminate memory errors, check your Java code for memory leaks. Eliminate references to objects that are no longer useful. For more information, see the Java SE Troubleshooting guide at <http://www.oracle.com/technetwork/java/javase/index-138283.html>.

## Pass Data to Java Methods

### In this section...

“Introduction” on page 10-66

“Conversion of MATLAB Argument Data” on page 10-66

“Passing Built-In Types” on page 10-68

“Converting Numbers to Integer Arguments” on page 10-69

“Passing String Arguments” on page 10-70

“Passing Java Objects” on page 10-70

“Other Data Conversion Topics” on page 10-73

“Passing Data to Overloaded Methods” on page 10-74

### Introduction

When you call a Java method, MATLAB types you pass in the call are converted to types native to the Java language. MATLAB performs this conversion on each argument that is passed, except for those arguments that are already Java objects. This section describes the conversion that is performed on specific MATLAB types and, at the end, also looks at how argument types affect calls made to overloaded methods.

If the method returns data, MATLAB converts the data to the appropriate MATLAB format. This process is covered in “Handle Data Returned from Java Methods” on page 10-76.

### Conversion of MATLAB Argument Data

MATLAB converts MATLAB data, passed as arguments to Java methods, into types that best represent the data to the Java language. The following table shows all of the MATLAB base types for passed arguments and the Java types defined for the parameters. Each row shows a MATLAB type followed by the possible Java argument matches, from left to right in order of closeness of the match. The MATLAB types (except cell arrays) can all be scalar (1-by-1) arrays or matrices. All of the Java types can be scalar values or arrays.

### Conversion of MATLAB Types to Java Types

MATLAB Argument	Java Parameter Type (Scalar or Array)						
	Closest Type <-----> Least Close Type						
logical	boolean	byte	short	int	long	float	double
double	double	float	long	int	short	byte	boolean
single	float	double					
char (1-by-1 scalar)	String	char					
char (1-by-n or n-by-1, n>1)	String	char[]					
char(m-by-n, m,n>1)	String[]						
uint8 int8	byte	short	int	long	float	double	
uint16 int16	short	int	long	float	double		
uint32 int32	int	long	float	double			
uint64 int64	long	float	double				
cell array of character vectors	String[]						
Java object	Object						
cell array of object	Object[]						
MATLAB object	Unsupported						

For more information about type conversion of arguments passed to Java code, see:

- “Passing Built-In Types” on page 10-68
- “Passing String Arguments” on page 10-70
- “Passing Java Objects” on page 10-70

## Passing Built-In Types

The Java language has eight types that are intrinsic to the language and are not represented as Java objects. These are often referred to as *built in*, or *elemental*, types and they include `boolean`, `byte`, `short`, `long`, `int`, `double`, `float`, and `char`. MATLAB converts its own types to these Java built-in types according to the table, Conversion of MATLAB Types to Java Types. Built-in types are in the first 10 rows of the table.

When a Java method you are calling expects one of these types, you can pass it the type of MATLAB argument shown in the leftmost column of the table. If the method takes an array of one of these types, you can pass a MATLAB array of the type. MATLAB converts the type of the argument to the type assigned in the method declaration.

The following MATLAB code creates a top-level window frame and sets its dimensions. The call to `setBounds` passes four MATLAB scalars of the `double` type to the inherited Java Frame method, `setBounds`, that takes four arguments of the `int` type. MATLAB converts each 64-bit double type to a 32-bit integer before calling the method.

The `setBounds` method declaration:

```
public void setBounds(int x, int y, int width, int height)
```

The MATLAB code that calls the method:

```
frame = java.awt.Frame;  
setBounds(frame,200,200,800,400)  
setVisible(frame,1)
```

## Passing Built-In Types in an Array

To call a Java method with an argument defined as an *array* of a built-in type, you can create and pass a MATLAB matrix with a compatible base type. The following code defines a polygon by sending four `x` and `y` coordinates to the Polygon constructor. Two 1-by-4 MATLAB arrays of `double` are passed to `java.awt.Polygon`, which expects integer arrays in the first two arguments. Shown here is the Java method declaration followed by MATLAB code that calls the method, and then verifies the set coordinates.

```
public Polygon(int xpoints[], int ypoints[], int npoints)  
  
poly = java.awt.Polygon([14 42 98 124], [55 12 -2 62], 4);  
[poly.xpoints poly.ypoints] % Verify the coordinates
```

```
ans =  
14    55  
42    12  
98    -2  
124   62
```

### **MATLAB Arrays Are Passed by Value**

Since MATLAB arrays are passed by value, any changes that a Java method makes to them are not visible to your MATLAB code. To access changes that a Java method makes to an array, then, rather than passing a MATLAB array, create and pass a Java array, which is a reference. For a description of using Java arrays in MATLAB, see “Java Arrays” on page 10-31.

---

**Note:** Generally, it is preferable to have methods return data that has been modified using the return argument mechanism as opposed to passing a reference to that data in an argument list.

---

### **Converting Numbers to Integer Arguments**

When passing an integer type to a Java method that takes a Java integer parameter, the MATLAB conversion is the same as the Java conversion between integer types. In particular, if the integer is out-of-range (does not fit into the number of bits of the parameter type), MATLAB discards all lowest  $n$  bits, where  $n$  is the number of bits in the parameter type. This is unlike conversion between MATLAB integer types, where out-of-range integers are converted to the maximum or minimum value represented by the destination type.

If the argument is floating point, MATLAB does not convert to an integer in the same manner as Java. A floating point number is first converted to a 64-bit signed integer with the fractional part truncated and then processed as if it were an `int64` argument.

When a floating point number is too large to be represented in a 64-bit integer (outside the range from  $-2^{63}$ – $2^{63}$ ), MATLAB converts the value as follows:

- Convert `int`, `short`, and `byte` parameter values to 0.
- Convert `long` parameter values to `java.lang.Long.MIN_VALUE`.
- Convert `Inf` and `-Inf` values to `-1`.
- Convert `NaN` values to 0.

## Passing String Arguments

To call a Java method that has an argument defined as an object of class `java.lang.String`, you can pass either a `String` object that was returned from an earlier Java call or a MATLAB 1-by-n character vector. If you pass the character vector, MATLAB converts it to a Java object of `java.lang.String` for you.

For a programming example, see “Read URL Using `java.net.URL`” on page 10-48. This example shows a MATLAB character array that holds a URL being passed to the Java `URL` class constructor. The following constructor expects a Java `String` argument.

```
public URL(String spec) throws MalformedURLException
```

In the MATLAB call to this constructor, a character array specifying the URL is passed. MATLAB converts this array to a Java `String` object before calling the constructor.

```
url = java.net.URL('http://archive.ncsa.uiuc.edu/demoweb/')
```

## Passing Strings in an Array

When the method you are calling expects an argument of an array of type `String`, you can create such an array by packaging the character vectors together in a MATLAB cell array. The character vectors can be of varying lengths since you are storing them in different cells of the array. As part of the method call, MATLAB converts the cell array to a Java array of `String` objects.

In the following example, the `echoPrompts` method of a user-written class accepts a string array argument that MATLAB converted from its original format as a cell array of character vectors. The parameter list in the Java method appears as follows:

```
public String[] echoPrompts(String s[])
```

You create the input argument by storing both character vectors in a MATLAB cell array. MATLAB converts this cell array to a Java array of `String`.

```
myaccount.echoPrompts({'Username: ', 'Password: '})  
ans =  
'Username: '  
'Password: '
```

## Passing Java Objects

When calling a method that has a parameter belonging to a Java class (other than `java.lang.Object`), you must pass a Java object that is an instance of that class.

MATLAB does not automatically convert MATLAB types to Java Object types. Unlike Java, MATLAB does not do autoboxing for numbers, such as converting double to Double.

In the example below, the add method belonging to the `java.awt.Menu` class requires, as an argument, an object of the `java.awt.MenuItem` class. The method declaration is:

```
public MenuItem add(MenuItem mi)
```

The example operates on the frame created in the previous example in “Passing Built-In Types” on page 10-68. The second, third, and fourth lines of code shown here add items to a menu to be attached to the existing window frame. In each of these calls to `menu1.add`, an object that is an instance of the `java.awt.MenuItem` Java class is passed.

```
menu1 = java.awt.Menu('File Options');
menu1.add(java.awt.MenuItem('New'));
menu1.add(java.awt.MenuItem('Open'));
menu1.add(java.awt.MenuItem('Save'));
```

```
menuBar=java.awt.MenuBar;
menuBar.add(menu1);
frame.setMenuBar(menuBar);
```

### Handling Objects of Class `java.lang.Object`

A special case exists when the method being called takes an argument of the `java.lang.Object` class. Since this class is the root of the Java class hierarchy, you can pass objects of any class in the argument. When passing a MATLAB argument, the argument is automatically converted to the closest Java Object type, which might include Java-style autoboxing, as shown in the following table.

MATLAB Argument	Java Object
logical	Boolean
double	Double
single	Float
char (1-by-1 scalar)	Character
char (1-by-n or n-by-1, n>1)	String
uint8 int8	Byte

MATLAB Argument	Java Object
uint16 int16	Short
uint32 int32	Integer
uint64 int64	Long
cell array of character vectors	String[ ]
Java object	Object
cell array of object	Object[ ]
MATLAB object	Unsupported

### Passing Objects in an Array

The only types of object arrays that you can pass to Java methods are Java arrays and MATLAB cell arrays. MATLAB automatically converts the cell array elements to `java.lang.Object` class objects. In order for a cell array to be passed from MATLAB, the corresponding argument in the Java method signature must specify `java.lang.Object` or an array of `java.lang.Object`.

If the objects are already in a Java array, either an array returned from a Java constructor or constructed in MATLAB by the `javaArray` function, then you simply pass it as the argument to the method being called. MATLAB does not convert the argument, because the argument is already a Java array.

The following example shows the `mapPoints` method of a user-written class accepting an array of `java.awt.Point` objects. The declaration for this method is:

```
public Object mapPoints(java.awt.Point p[])
```

The following MATLAB code creates a 4-by-1 array containing four Java `Point` objects. When the array is passed to the `mapPoints` method, no conversion is necessary because the `javaArray` function created a Java array of `java.awt.Point` objects.

```
pointObj = javaArray('java.awt.Point',4);
pointObj(1) = java.awt.Point(25,143);
pointObj(2) = java.awt.Point(31,147);
pointObj(3) = java.awt.Point(49,151);
pointObj(4) = java.awt.Point(52,176);
```



```
testData.mapPoints(pointObj);
```

### Handling a Cell Array of Java Objects

You create a cell array of Java objects by using the MATLAB syntax `{a1,a2,...}`. You index into a cell array of Java objects in the usual way, with the syntax `a{m,n,...}`.

The following example creates a cell array of two `Frame` objects, `frame1` and `frame2`, and assigns it to variable `frameArray`.

```
frame1 = java.awt.Frame('Frame A');
frame2 = java.awt.Frame('Frame B');
```

```
frameArray = {frame1, frame2}
```

```
frameArray =
[1x1 java.awt.Frame]    [1x1 java.awt.Frame]
```

The next statement assigns element `{1,2}` of the cell array `frameArray` to variable `f`.

```
f = frameArray {1,2}
```

```
f =
java.awt.Frame[frame2,0,0,0x0,invalid,hidden,layout =
java.awt.BorderLayout,resizable,title=Frame B]
```

### Other Data Conversion Topics

There are several remaining items of interest regarding the way MATLAB converts its data to a compatible Java type. This includes how MATLAB matches array dimensions, and how it handles empty matrices and empty character vectors.

#### How Array Dimensions Affect Conversion

The term *dimension* refers to the number of subscripts required to address the elements of an array. For example, a 5-by-1 array has one dimension, because you can index individual elements using only one array subscript.

In converting MATLAB to Java arrays, MATLAB handles dimension in a special manner. For a MATLAB array, dimension can be considered as the number of nonsingleton dimensions in the array. For example, a 10-by-1 array has dimension 1, and a 1-by-1 array has dimension 0. In Java code, dimension is determined solely by the

number of nested arrays. For example, `double[ ][ ]` has dimension 2, and `double` has dimension 0.

If the number of dimensions of the Java array exactly matches the MATLAB array's number of dimensions  $n$ , the conversion results in a Java array with  $n$  dimensions. If the Java array has fewer than  $n$  dimensions, the conversion drops singleton dimensions, starting with the first one, until the number of remaining dimensions matches the number of dimensions in the Java array.

### **Empty Matrices and Nulls**

An empty matrix is converted to a Java `null`. The empty character ( ' ' ) in MATLAB translates into an empty (not `null`) `String` object in Java code. Empty (0-length) Java arrays remain unchanged.

## **Passing Data to Overloaded Methods**

When you invoke an overloaded method on a Java object, MATLAB determines which method to invoke by comparing the arguments your call passes to the arguments defined for the methods. In this discussion, the term *method* includes constructors. When it determines the method to call, MATLAB converts the calling arguments to Java method types according to Java conversion rules, except for conversions involving objects or cell arrays. See “Passing Objects in an Array” on page 10-72.

### **How MATLAB Determines the Method to Call**

When your MATLAB function calls a Java method, MATLAB:

- 1 Checks to make sure that the object (or class, for a static method) has a method by that name.
- 2 Determines whether the invocation passes the same number of arguments of at least one method with that name.
- 3 Makes sure that each passed argument can be converted to the Java type defined for the method.

If all of the preceding conditions are satisfied, MATLAB calls the method.

In a call to an overloaded method, if there is more than one candidate, MATLAB selects the one with arguments that best fit the calling arguments. First, MATLAB rejects all methods that have any argument types that are incompatible with the passed arguments

(for example, if the method has a `double` argument and the passed argument is a `char` type).

Among the remaining methods, MATLAB selects the one with the highest fitness value, which is the sum of the fitness values of all its arguments. The fitness value for each argument is the fitness of the base type minus the difference between the MATLAB array dimension and the Java array dimension. (Array dimensionality is explained in “How Array Dimensions Affect Conversion” on page 10-73.) If two methods have the same fitness, the first one defined in the Java class is chosen.

### Example — Calling an Overloaded Method

Suppose that a function constructs a `java.io.OutputStreamWriter` object, `osw`, and then invokes a method on the object.

```
osw.write('Test data', 0, 9);
```

MATLAB finds that the class `java.io.OutputStreamWriter` defines three `write` methods.

```
public void write(int c);
public void write(char[] cbuf, int off, int len);
public void write(String str, int off, int len);
```

MATLAB rejects the first `write` method, because it takes only one argument. Then, MATLAB assesses the fitness of the remaining two `write` methods. These differ only in their first argument, as explained below.

In the first of these two `write` methods, the first argument is defined with base type, `char`. The table, Conversion of MATLAB Types to Java Types, shows that for the type of the calling argument (MATLAB `char`), Java type, `char`, has a value of 6. There is no difference between the dimension of the calling argument and the Java argument. So the fitness value for the first argument is 6.

In the other `write` method, the first argument has Java type `String`, which has a fitness value of 7. The dimension of the Java argument is 0, so the difference between it and the calling argument dimension is 1. Therefore, the fitness value for the first argument is 6.

Because the fitness value of those two `write` methods is equal, MATLAB calls the one listed first in the class definition, with `char[]` first argument.

## Handle Data Returned from Java Methods

### In this section...

“Introduction” on page 10-76

“Conversion of Java Return Types” on page 10-76

“Conversion of Java Object Return Types” on page 10-77

“Built-In Types” on page 10-78

“Converting Objects to MATLAB Types” on page 10-78

### Introduction

In many cases, data returned from a Java method is incompatible with the types operated on in the MATLAB platform. When this is the case, MATLAB converts the returned value to a type native to the MATLAB language. This section describes the conversion performed on the various types that can be returned from a call to a Java method.

### Conversion of Java Return Types

The following table lists Java return types and the resulting MATLAB types. For some Java base return types, MATLAB treats scalar and array returns differently. For information about `java.lang.Object` type, see “Conversion of Java Object Return Types” on page 10-77.

#### Conversion of Java Types to MATLAB Types

Java Return Type	If Scalar Return, Resulting MATLAB Type	If Array Return, Resulting MATLAB Type
boolean	logical	logical
byte	double	int8
short	double	int16
int	double	int32
long	double	int64
float	double	single
double	double	double

Java Return Type	If Scalar Return, Resulting MATLAB Type	If Array Return, Resulting MATLAB Type
char	char	char

---

**Note:** MATLAB converts rectangular Java arrays to arrays of the resulting type. When Java returns a nonrectangular (jagged) array, MATLAB converts it to a cell array. For more information, see “How MATLAB Represents the Java Array” on page 10-31.

---

## Conversion of Java Object Return Types

When a Java method is declared to return data of type `java.lang.Object`, MATLAB converts its value, depending on its actual type, according to the following table.

There is no conversion if the method declaration specifies any subclass of `Object` or array of `Object`. For example, if the method is declared to return `java.lang.String`, then the return value remains a `java.lang.String` object and is not automatically converted to `char` as is shown in the table.

Other object types, including `Object` arrays, are not converted; they remain Java objects. However, if you index into a returned `Object` array, the value is converted according to the table.

For more information, see “Elements of `java.lang.Object` Arrays Are Converted to MATLAB Types” on page 10-41.

### Conversion of `java.lang.Object` Type to MATLAB Types

Actual Java Type	Return Scalar MATLAB Type
<code>java.lang.Boolean</code>	logical
<code>java.lang.Byte</code>	double
<code>java.lang.Short</code>	double
<code>java.lang.Integer</code>	double
<code>java.lang.Long</code>	double
<code>java.lang.Float</code>	double
<code>java.lang.Double</code>	double
<code>java.lang.Character</code>	char

Actual Java Type	Return Scalar MATLAB Type
<code>java.lang.String</code>	<code>char</code>

## Built-In Types

Java *built-in* types are described in “Passing Built-In Types” on page 10-68. This type includes `boolean`, `byte`, `short`, `long`, `int`, `double`, `float`, and `char`. When the value returned from a method call is one of these types, MATLAB converts it according to the table Conversion of Java Types to MATLAB Types.

A single numeric or `boolean` value converts to a 1-by-1 matrix of `double`, which is convenient for use in MATLAB. An array of a numeric or `boolean` return values converts each member of the array to the closest base type to minimize the required storage space. Array member conversions are listed in the right-hand column of the table.

A return value of Java type `char` converts to a 1-by-1 matrix of `char`. An array of Java `char` converts to a MATLAB array of that type.

## Converting Objects to MATLAB Types

Except for objects of class `Object`, MATLAB does not convert Java objects returned from method calls to a native MATLAB type. If you want to convert Java object data to a form more readily usable in MATLAB, there are a few MATLAB functions that enable you to do this. These are described in the following sections.

- “Converting to the MATLAB double Type” on page 10-78
- “Converting to the MATLAB char Type” on page 10-79
- “Converting to a MATLAB Structure” on page 10-80
- “Converting to a MATLAB Cell Array” on page 10-80

### Converting to the MATLAB double Type

Using the `double` function in MATLAB, you can convert any Java object or array of objects to the MATLAB `double` type. The action taken by the `double` function depends on the class of the object you specify:

- If the object is an instance of a numeric class (`java.lang.Number` or one of the classes that inherit from that class), MATLAB uses a preset conversion algorithm to convert the object to a MATLAB `double`.

- If the object is not an instance of a numeric class, MATLAB checks the class definition to see if it implements a method called `toDouble`. MATLAB uses `toDouble` to perform its conversion of Java objects to the MATLAB `double` type. If such a method is implemented for this class, MATLAB executes it to perform the conversion.
- If you are using a class of your own design, you can write your own `toDouble` method to perform conversions on objects of that class to a MATLAB `double`. This enables you to specify your own means of type conversion for objects belonging to your own classes.

---

**Note:** If the class of the specified object is not `java.lang.Number`, does not inherit from that `java.lang.Number`, and does not implement a `toDouble` method, then an attempt to convert the object using the `double` function results in a MATLAB error message.

---

The syntax for the `double` command is as follows, where `object` is a Java object or Java array of objects:

```
double(object);
```

### Converting to the MATLAB char Type

With the MATLAB `char` function, you can convert `java.lang.String` objects and arrays to MATLAB character arrays.

The syntax for the `char` command is as follows, where `object` is a Java object or Java array of objects:

```
char(object);
```

If the object specified in the `char` command is not an instance of the `java.lang.String` class, MATLAB checks its class to see if it implements a method named `toChar`. If so, MATLAB executes the `toChar` method of the class to perform the conversion. If you write your own class definitions, you can use this feature by writing a `toChar` method that performs the conversion according to your own needs.

---

**Note:** If the class of the specified object is not `java.lang.String` and it does not implement a `toChar` method, an attempt to convert the object using the `char` function results in a MATLAB error message.

---

### Converting to a MATLAB Structure

Java objects are similar to the MATLAB `struct` type in that many of an object's characteristics are accessible via field names defined within the object. You might want to convert a Java object into a MATLAB `struct` to facilitate the handling of its data in MATLAB. Use the MATLAB `struct` function to do this.

The syntax for the `struct` command is as follows, where `object` is a Java object or a Java array of objects:

```
struct(object);
```

The following example converts a `java.awt.Polygon` object into a MATLAB `struct`. You can access the fields of the object directly using MATLAB `struct` operations. The last line indexes into the array, `pstruct.xpoints`, to deposit a new value into the third array element.

```
polygon = java.awt.Polygon([14 42 98 124], [55 12 -2 62], 4);  
pstruct = struct(polygon)
```

```
pstruct =  
    npoints: 4  
    xpoints: [4x1 int32]  
    ypoints: [4x1 int32]
```

```
pstruct.xpoints
```

```
ans =  
    14  
    42  
    98  
   124
```

```
pstruct.xpoints(3) = 101;
```

### Converting to a MATLAB Cell Array

Use the `cell` function to convert a Java array or Java object into a MATLAB cell array. Elements of the resulting cell array are of the MATLAB type (if any) closest to the Java array elements or Java object.

The syntax for the `cell` command is as follows, where `object` is a Java object or a Java array of objects.

```
cell(object);
```



The following example uses the `cell` command to create a MATLAB cell array in which each cell holds an array of a different type.

```
import java.lang.* java.awt.*;

% Create a Java array of double
dblArray = javaArray('java.lang.Double', 1, 10);
for m = 1:10
    dblArray(1, m) = Double(m * 7);
end

% Create a Java array of points
ptArray = javaArray('java.awt.Point', 3);
ptArray(1) = Point(7.1, 22);
ptArray(2) = Point(5.2, 35);
ptArray(3) = Point(3.1, 49);

% Create a Java array of strings
strArray = javaArray('java.lang.String', 2, 2);
strArray(1,1) = String('one');    strArray(1,2) = String('two');
strArray(2,1) = String('three');  strArray(2,2) = String('four');

% Convert each to cell arrays
cellArray = {cell(dblArray), cell(ptArray), cell(strArray)}
cellArray =
    {1x10 cell}    {3x1 cell}    {2x2 cell}

cellArray{1,1}    % Array of type double
ans =

    [7]    [14]    [21]    [28]    [35]    [42]    [49]    [56]    [63]    [70]

cellArray{1,2}    % Array of type Java.awt.Point
ans =
    [1x1 java.awt.Point]
    [1x1 java.awt.Point]
    [1x1 java.awt.Point]

cellArray{1,3}    % Array of type char array
ans =
    'one'        'two'
    'three'     'four'
```



# Using .NET Libraries from MATLAB

---

- “Read Cell Arrays of Excel Spreadsheet Data” on page 11-4
- “Access a Simple .NET Class” on page 11-6
- “Load a Global .NET Assembly” on page 11-12
- “Work with Microsoft Excel Spreadsheets Using .NET” on page 11-13
- “Work with Microsoft Word Documents Using .NET” on page 11-15
- “Assembly is Library of .NET Classes” on page 11-16
- “Limitations to .NET Support” on page 11-17
- “System Requirements for Using MATLAB Interface to .NET” on page 11-19
- “Using .NET from MATLAB” on page 11-20
- “Using a .NET Object” on page 11-22
- “Build a .NET Application for MATLAB Examples” on page 11-24
- “Troubleshooting Security Policy Settings from Network Drives” on page 11-25
- “.NET Terminology” on page 11-26
- “Simplify .NET Class Names” on page 11-27
- “Use import in MATLAB Functions” on page 11-28
- “Nested Classes” on page 11-29
- “Handle .NET Exceptions” on page 11-30
- “Pass Numeric Arguments” on page 11-31
- “Pass System.String Arguments” on page 11-32
- “Pass System.Enum Arguments” on page 11-34
- “Pass System.Nullable Arguments” on page 11-36
- “Pass Cell Arrays of .NET Data” on page 11-40
- “Pass Jagged Arrays” on page 11-43
- “Convert Nested System.Object Arrays” on page 11-46
- “Pass Data to .NET Objects” on page 11-47

- “Handle Data Returned from .NET Objects” on page 11-54
- “Use Arrays with .NET Applications” on page 11-59
- “Convert .NET Arrays to Cell Arrays” on page 11-61
- “Limitations to Support of .NET Arrays” on page 11-64
- “Set Static .NET Properties” on page 11-65
- “Using .NET Properties” on page 11-67
- “MATLAB Does Not Display Protected Properties” on page 11-69
- “Work with .NET Methods Having Multiple Signatures” on page 11-70
- “Call .NET Methods With `out` Keyword” on page 11-72
- “Call .NET Methods With `ref` Keyword” on page 11-74
- “Call .NET Methods With `params` Keyword” on page 11-76
- “Call .NET Methods with Optional Arguments” on page 11-78
- “Calling .NET Methods” on page 11-81
- “Calling .NET Methods with Optional Arguments” on page 11-84
- “Calling .NET Extension Methods” on page 11-85
- “Call .NET Properties That Take an Argument” on page 11-86
- “How MATLAB Represents .NET Operators” on page 11-88
- “Limitations to Support of .NET Methods” on page 11-89
- “Use .NET Events in MATLAB” on page 11-90
- “Call .NET Delegates in MATLAB” on page 11-93
- “Create Delegates from .NET Object Methods” on page 11-95
- “Create Delegate Instances Bound to .NET Methods” on page 11-96
- “.NET Delegates With `out` and `ref` Type Arguments” on page 11-98
- “Combine and Remove .NET Delegates” on page 11-99
- “.NET Delegates” on page 11-101
- “Calling .NET Methods Asynchronously” on page 11-102
- “Limitations to Support of .NET Events” on page 11-106
- “Limitations to Support of .NET Delegates” on page 11-107
- “Use Bit Flags with .NET Enumerations” on page 11-108
- “Read Special System Folder Path” on page 11-112

- “.NET Enumerations in MATLAB” on page 11-113
- “Default Methods for an Enumeration” on page 11-114
- “NetDocEnum Example Assembly” on page 11-116
- “Work with Members of a .NET Enumeration” on page 11-117
- “Refer to a .NET Enumeration Member” on page 11-119
- “Display .NET Enumeration Members as Character Vectors” on page 11-121
- “Convert .NET Enumeration Values to Type Double” on page 11-122
- “Iterate Through a .NET Enumeration” on page 11-123
- “Use .NET Enumerations to Test for Conditions” on page 11-125
- “Underlying Enumeration Values” on page 11-127
- “Limitations to Support of .NET Enumerations” on page 11-128
- “Create .NET Collections” on page 11-129
- “Convert .NET Collections to MATLAB Arrays” on page 11-131
- “Create .NET Arrays of Generic Type” on page 11-132
- “Display .NET Generic Methods Using Reflection” on page 11-133
- “.NET Generic Classes” on page 11-136
- “Accessing Items in .NET Collections” on page 11-137
- “Call .NET Generic Methods” on page 11-138

## Read Cell Arrays of Excel Spreadsheet Data

This example shows how to convert columns of Microsoft Excel<sup>®</sup> spreadsheet data to MATLAB types. MATLAB reads a range of .NET values as a `System.Object[,]` type. Use the `cell` function to convert `System.String` values to MATLAB character arrays and `System.DateTime` values to `datetime` objects.

Create a file in Excel that contains the following data.

Date	Weight
10/31/96	174.8
11/29/96	179.3
12/30/96	190.4
01/31/97	185.7

Right-click the **Date** column, select **Format Cells**, and then the **Number** tab. Verify that the value for **Category:** is **Date**.

Name the file `weight.xls` in the `H:\Documents\MATLAB` folder. Close the file.

In MATLAB, read the data from the spreadsheet.

```
NET.addAssembly('microsoft.office.interop.excel');
app = Microsoft.Office.Interop.Excel.ApplicationClass;
book = app.Workbooks.Open('H:\Documents\MATLAB\weight.xls');
sheet = Microsoft.Office.Interop.Excel.Worksheet(book.Worksheets.Item(1));
range = sheet.UsedRange;
arr = range.Value;
```

Convert the data to MATLAB types.

```
data = cell(arr, 'ConvertTypes', {'all'});
```

Display the dates.

```
cellfun(@disp, data(:, 1))
```

```
Date
    31-Oct-1996 00:00:00
    29-Nov-1996 00:00:00
    30-Dec-1996 00:00:00
```

31-Jan-1997 00:00:00

Quit the Excel program.

Close (book)

Quit (app)

## **Related Examples**

- “Read Spreadsheet Data Using Excel as Automation Server” on page 12-15

## **More About**

- “Convert .NET Arrays to Cell Arrays” on page 11-61
- “Spreadsheets”

## Access a Simple .NET Class

### In this section...

“System.DateTime Example” on page 11-6

“Create .NET Object From Constructor” on page 11-7

“View Information About .NET Object” on page 11-7

“Introduction to .NET Data Types” on page 11-9

### System.DateTime Example

This example shows how to access functionality already loaded on your system. The topics following the example introduce some key steps and ideas to help you get started using .NET in MATLAB.

The Microsoft .NET Framework class library contains classes, such as `System.DateTime`, you can use in MATLAB. The following code creates an object and uses `DateTime` properties and methods to display information about the current date and time.

```
% Create object for current date and time
netDate = System.DateTime.Now;

% Display properties
netDate.DayOfWeek
netDate.Hour

% Call methods
ToShortTimeString(netDate)
AddDays(netDate,7);

% Call static method
System.DateTime.DaysInMonth(netDate.Year,netDate.Month)
```

The following topics provide more information about creating and viewing information about objects and an introduction to .NET data types.

For information about the .NET Framework class library, refer to the third party documentation described in “To Learn More About the .NET Framework” on page 11-21.



## Create .NET Object From Constructor

The example in the previous section uses the `Now` property to create a `DateTime` object. The following example shows how to create an object using one of the `DateTime` constructors.

```
myDate = System.DateTime(2000,1,31);
```

To call this constructor, or any method, you need to know its argument list, or *function signature*. Your vendor product documentation shows the function signatures. You can also display the signatures using the MATLAB `methodsview` function. Type `methodsview('System.DateTime')` and search the list for `DateTime` entries, such as shown in the following table.

Return Type	Name	Arguments
System.DateTime obj	DateTime	(int32 scalar year,...)

From the .NET Class Framework documentation, the following signature initializes a new instance of the `DateTime` structure to the specified year, month, and day, which is the information required for the `myDate` variable.

Return Type	Name	Arguments
System.DateTime obj	DateTime	(int32 scalar year, int32 scalar month, int32 scalar day)

For more information, see “Reading Method Signatures” on page 11-82.

## View Information About .NET Object

Although the vendor documentation contains information about `DateTime` objects, you can use MATLAB commands, like `properties` and `methods`, to display information about .NET objects. For example:

```
% Display an object
netDate = System.DateTime.Now
% Display its properties
properties System.DateTime
% Display its methods
```

methods [System.DateTime](#)

MATLAB displays the following information. (The property values reflect your specific date and time.)

### Display of DateTime Object

```
netDate =  
    System.DateTime  
    Package: System  
  
Properties:  
    Date: [1x1 System.DateTime]  
    Day: 11  
    DayOfWeek: [1x1 System.DayOfWeek]  
    DayOfYear: 11  
    Hour: 12  
    Kind: [1x1 System.DateTimeKind]  
    Millisecond: 413  
    Minute: 31  
    Month: 1  
    Now: [1x1 System.DateTime]  
    UtcNow: [1x1 System.DateTime]  
    Second: 38  
    Ticks: 634303458984133595  
    TimeOfDay: [1x1 System.TimeSpan]  
    Today: [1x1 System.DateTime]  
    Year: 2011  
    MinValue: [1x1 System.DateTime]  
    MaxValue: [1x1 System.DateTime]  
Methods, Superclasses
```

### Display of DateTime Properties

Properties for class System.DateTime:

```
Date  
Day  
DayOfWeek  
DayOfYear  
Hour  
Kind  
Millisecond  
Minute  
Month
```

```

Now
UtcNow
Second
Ticks
TimeOfDay
Today
Year
MinValue
MaxValue

```

### Display of DateTime Methods

Methods for class System.DateTime:

Add	GetType	ToUniversalTime
AddDays	GetTypeCode	addlistener
AddHours	IsDaylightSavingTime	delete
AddMilliseconds	Subtract	eq
AddMinutes	ToBinary	findobj
AddMonths	ToFileTime	findprop
AddSeconds	ToFileTimeUtc	ge
AddTicks	ToLocalTime	gt
AddYears	ToLongDateString	isvalid
CompareTo	ToLongTimeString	le
DateTime	ToOADate	lt
Equals	ToShortDateString	ne
GetDateTimeFormats	ToShortTimeString	notify
GetHashCode	ToString	

Static methods:

Compare	Parse	op_GreaterThan
DaysInMonth	ParseExact	op_GreaterThanOrEqual
FromBinary	SpecifyKind	op_Inequality
FromFileTime	TryParse	op_LessThan
FromFileTimeUtc	TryParseExact	op_LessThanOrEqual
FromOADate	op_Addition	op_Subtraction
IsLeapYear	op_Equality	

For more information, see:

- “Using .NET Properties” on page 11-67
- “Calling .NET Methods” on page 11-81

## Introduction to .NET Data Types

To use .NET objects in MATLAB, you need to understand how MATLAB treats .NET data types. For example, the following `DateTime` properties and methods create variables of various .NET types:

```
netDate = System.DateTime.Now;
thisDay = netDate.DayOfWeek;
thisHour = netDate.Hour;
thisDate = ToLongDateString(netDate);
thisTime = ToShortTimeString(netDate);
monthSz = System.DateTime.DaysInMonth(netDate.Year,netDate.Month);
whos
```

Name	Size	Bytes	Class
netDate	1x1	112	System.DateTime
monthSz	1x1	4	int32
thisDate	1x1	112	System.String
thisDay	1x1	104	System.DayOfWeek
thisHour	1x1	4	int32
thisTime	1x1	112	System.String

MATLAB displays the type as a class name.

To use these variables in MATLAB, consider the following:

- Numeric values (`int32`) — MATLAB preserves .NET numeric types by mapping them into equivalent MATLAB types. In the following example, `h` is type `int32`.

```
h = thisHour + 1;
```

For more information, see “.NET Type to MATLAB Type Mapping” on page 11-54 and “Numeric Types”.

- Strings (`System.String`) — Use the `char` function to convert a `System.String` object to a MATLAB char array:

```
disp(['The time is ' char(thisTime)])
```

- Objects (`System.DateTime`) — Refer to the .NET Framework class library documentation for information about using a `DateTime` object.
- Enumerations (`System.DayOfWeek`) — According to the `DateTime` documentation, `DayOfWeek` is an enumeration. To display the enumeration members, type:

```
enumeration(thisDay)
```

For more information, see “Enumerations”.

For a complete list of supported types and mappings, see “Handle Data Returned from .NET Objects” on page 11-54.

## **More About**

- “To Learn More About the .NET Framework” on page 11-21
- “Reading Method Signatures” on page 11-82
- “.NET Type to MATLAB Type Mapping” on page 11-54
- “Handle Data Returned from .NET Objects” on page 11-54

## Load a Global .NET Assembly

This example shows you how to make .NET classes visible to MATLAB by loading a global assembly using the `NET.addAssembly` function.

The speech synthesizer class (available in .NET Framework Version 3.0 and above) provides ready-to-use text-to-speech features. For example, type:

```
NET.addAssembly('System.Speech');  
speak = System.Speech.Synthesis.SpeechSynthesizer;  
speak.Volume = 100;  
Speak(speak, 'You can use .NET Libraries in MATLAB')
```

The speech synthesizer class, like any .NET class, is part of an *assembly*. To work with the class, call `NET.addAssembly` to load the assembly into MATLAB. Your vendor documentation contains the assembly name. For example, search the Microsoft .NET Framework website for the `System.SpeechSynthesizer` class. The assembly name is `System.Speech`.

```
NET.addAssembly('System.Speech');
```

The `System.Speech` assembly is a *global* assembly. If your assembly is a *private* assembly, use the full path for the input to `NET.addAssembly`.

The “System.DateTime Example” on page 11-6 does not call `NET.addAssembly` because MATLAB dynamically loads its assembly (`mscorlib`) at startup.

---

**Note:** You cannot unload an assembly in MATLAB.

---

### See Also

`NET.addAssembly`

### More About

- “Assembly is Library of .NET Classes” on page 11-16

## Work with Microsoft Excel Spreadsheets Using .NET

This example creates a spreadsheet, copies some MATLAB data to it, and closes it. The example uses classes from the `Microsoft.Office.Interop.Excel.ApplicationClass` class. For information about the class and using the interface with different versions of Excel, refer to documentation on the MSDN website <http://msdn.microsoft.com/>.

To create a workbook, type:

```
NET.addAssembly('microsoft.office.interop.excel');
app = Microsoft.Office.Interop.Excel.ApplicationClass;
books = app.Workbooks;
newWB = Add(books);
app.Visible = true;
```

Create a new sheet:

```
sheets = newWB.Worksheets;
newSheet = Item(sheets,1);
```

`newSheet` is a `System.__ComObject` because `sheets.Item` can return different types, such as a `Chart` or a `Worksheet`. To make the sheet a `Worksheet`, use the command:

```
newWS = Microsoft.Office.Interop.Excel.Worksheet(newSheet);
```

Create MATLAB data and write columns 1 and 2 to a range of cells.

```
excelArray = rand(10);
newRange = Range(newWS, 'A1');
newRange.Value2 = 'Data from Location A';
newRange = Range(newWS, 'A3:B12');
newRange.Value2 = excelArray;
```

Add three text strings to column C.

```
% Create a 3x1 System.Object
strArray = NET.createArray('System.Object',3,1);
strArray(1,1) = 'Add';
strArray(2,1) = 'text';
strArray(3,1) = 'to column C';
newRange = Range(newWS, 'C3:C5');
newRange.Value2 = strArray;
```

Modify cell format and name the worksheet:

```
newFont = newRange.Font;  
newFont.Bold = 1;  
newWS.Name = 'Test Data';
```

If this is a new spreadsheet, use the `SaveAs` method:

```
SaveAs(newWB, 'mySpreadsheet.xlsx');
```

Close and quit:

```
Close(newWB)  
Quit(app)
```

### Related Examples

- “Work with Microsoft Word Documents Using .NET” on page 11-15

### External Websites

- <http://msdn.microsoft.com/>



## Work with Microsoft Word Documents Using .NET

This example uses classes from the `Microsoft.Office.Interop.Word.ApplicationClass` class. For information about the class and using the interface with different versions of Microsoft Word, refer to documentation on the MSDN website <http://msdn.microsoft.com/>.

The following code creates a new Word document:

```
NET.addAssembly('microsoft.office.interop.word');  
wordApp = Microsoft.Office.Interop.Word.ApplicationClass;  
wordDoc = wordApp.Documents;  
newDoc = Add(wordDoc);
```

If you want to type directly into the document, type the MATLAB command:

```
wordApp.Visible = true;
```

Put the cursor into the document window and enter text.

To name the document `myDocument.docx` and save it in the My Documents folder, type:

```
SaveAs(newDoc, 'myDocument.docx');
```

When you are finished, to close the document and application, type:

```
Save(newDoc);  
Close(newDoc);  
Quit(wordApp);
```

### Related Examples

- “Work with Microsoft Excel Spreadsheets Using .NET” on page 11-13

### External Websites

- <http://msdn.microsoft.com/>

## Assembly is Library of .NET Classes

Assemblies are the building blocks of .NET Framework applications; they form the fundamental unit of deployment, version control, reuse, activation scoping, and security permissions. An *assembly* is a collection of types and resources built to work together and form a logical unit of functionality.

To work with a .NET application, you need to make its assemblies visible to MATLAB. How you do this depends on how the assembly is deployed, either privately or globally.

- *global* assembly—Shared among applications and installed in a common directory, called the *Global Assembly Cache* (GAC).
- *private* assembly—Used by a single application.

To load a global assembly into MATLAB, use the short name of the assembly, which is the file name without the extension. To load a private assembly, you need the *full path* (folder and file name with extension) of the assembly. This information is in the vendor documentation for the assembly. Refer to the vendor documentation for information about using your product.

The following assemblies from the .NET Framework class library are available at startup. MATLAB dynamically loads them the first time you type “NET.” or “System.”.

- `mscorlib.dll`
- `system.dll`

To use any other .NET assembly, load the assembly using the `NET.addAssembly` command. After loading the assembly, you can work with the classes defined by the assembly.

---

**Note:** You cannot unload an assembly in MATLAB. If you modify and rebuild your own assembly, you must restart MATLAB to access the changes.

---

### See Also

`NET.addAssembly`

## Limitations to .NET Support

MATLAB supports the .NET features C# supports, except for the limits noted in the following table.

Features Not Supported in MATLAB
Cannot use <code>ClassName.propertyname</code> syntax to set static properties. Use <code>NET.setStaticProperty</code> instead.
Unloading an assembly
Passing a structure array, sparse array, or complex number to a .NET property or method
Subclassing .NET classes from MATLAB
Accessing nonpublic class members
Displaying generic methods using <code>methods</code> or <code>methodsview</code> functions. For a workaround, see “Display .NET Generic Methods Using Reflection” on page 11-133.
Creating an instance of a nested class. For a workaround, see “Nested Classes” on page 11-29.
Saving (serializing) .NET objects into a MAT-file
Creating .NET arrays with a specific lower bound
Concatenating multiple .NET objects into an array
Implementing interface methods
Hosting .NET controls in figure windows
Casting operations
Calling constructors with <code>ref</code> or <code>out</code> type arguments
Using <code>System.Console.WriteLine</code> to write text to the command window
Pointer type arguments, function pointers, <code>Dllimport</code> keyword
.NET remoting
Using the MATLAB <code>:</code> (colon) operator in a <code>foreach</code> iteration
Adding event listeners to .NET events defined in static classes
Handling .NET events with signatures that do not conform to the standard signature
Creating empty .NET objects

## Features Not Supported in MATLAB

Creating .NET objects that do not belong to a namespace

### More About

- “Limitations to Support of .NET Arrays” on page 11-64
- “Limitations to Support of .NET Methods” on page 11-89
- “Limitations to Support of .NET Events” on page 11-106
- “Limitations to Support of .NET Delegates” on page 11-107
- “Limitations to Support of .NET Enumerations” on page 11-128
- “System Requirements for Using MATLAB Interface to .NET” on page 11-19

## System Requirements for Using MATLAB Interface to .NET

The MATLAB interface to .NET is available on the Windows platform only.

You must have the Microsoft .NET Framework installed on your system.

The MATLAB interface requires the .NET Framework Version 4.0 and above. The interface continues to support assemblies built on Framework 2.0 and above. To determine if your system has the supported framework, use the `NET.IsNETSupported` function.

To use a .NET application, refer to your vendor's product documentation for information about how to install the program and for details about its functionality.

### MATLAB Configuration File

MATLAB provides a configuration file, `MATLAB.exe.config`, in your `matlabroot/bin/64` folder. With this file, MATLAB loads the latest core assemblies available on your system. You can modify and use the configuration file at your own risk. For additional information on elements that can be used in the configuration file, visit the Configuration File Schema for the .NET Framework website at <http://msdn.microsoft.com/en-us/library/1fk1t1t0.aspx>.

### More About

- “Limitations to .NET Support” on page 11-17

## Using .NET from MATLAB

### In this section...

“Benefits of the MATLAB .NET Interface” on page 11-20

“Why Use the MATLAB .NET Interface?” on page 11-20

“NET Assembly Integration Using MATLAB Compiler SDK” on page 11-21

“To Learn More About the .NET Framework” on page 11-21

### Benefits of the MATLAB .NET Interface

The MATLAB .NET interface enables you to:

- Create instances of .NET classes.
- Interact with .NET applications via their class members.

### Why Use the MATLAB .NET Interface?

Use the MATLAB .NET interface to take advantage of the capabilities of the Microsoft .NET Framework. For example:

- You have a professionally developed .NET assembly and want to use it to do certain operations, such as access hardware.
- You want to leverage the capabilities of programming in .NET (for example, you have existing C# programs).
- You want to access existing Microsoft-supplied classes for .NET.

The speech synthesizer class, available in .NET Framework Version 3.0 and above, is an example of a ready-to-use feature. Create the following `Speak` function in MATLAB:

```
function Speak(text)
NET.addAssembly('System.Speech');
speak = System.Speech.Synthesis.SpeechSynthesizer;
speak.Volume = 100;
Speak(speak, text)
end
```

For an example rendering text to speech, type:

```
Speak('You can use .NET Libraries in MATLAB')
```

## NET Assembly Integration Using MATLAB Compiler SDK

The MATLAB .NET interface is for MATLAB users who want to use .NET assemblies in MATLAB.

NET Assembly Integration in the MATLAB Compiler SDK product packages MATLAB functions so that .NET programmers can access them. It brings MATLAB into .NET applications. For information about NET Assembly Integration, see the MATLAB Compiler SDK product documentation.

## To Learn More About the .NET Framework

For a complete description of the .NET Framework, you need to consult outside resources.

One source of information is the Microsoft Developer Network. Search the .NET Framework Development Center at <http://msdn.microsoft.com/en-us/netframework/aa496123> for the term “.NET Framework Class Library”. The .NET Framework Class Library is a programming reference manual. Many examples in this documentation refer to classes in this library. There are different versions of the .NET Framework documentation, so be sure to refer to the version that is on your system. See “System Requirements for Using MATLAB Interface to .NET” on page 11-19 for information about version support in MATLAB.

## More About

- “Limitations to .NET Support” on page 11-17

## Using a .NET Object

### In this section...

“Creating a .NET Object” on page 11-22

“What Classes Are in a .NET Assembly?” on page 11-22

“Using the delete Function on a .NET Object” on page 11-23

### Creating a .NET Object

You often create objects when working with .NET classes. An *object* is an instance of a particular class. Methods are functions that operate exclusively on objects of a class. Data types package together objects and methods so that the methods operate on objects of their own type. For information about using objects in MATLAB, see “Operations on Objects”.

You construct .NET objects in the MATLAB workspace by calling the class constructor, which has the same name as the class. The syntax to create a .NET object `classObj` is:

```
classObj = namespace.ClassName(varargin)
```

where `varargin` is the list of constructor arguments to create an instance of the class specified by `ClassName` in the given `namespace`. For an example, see “Create .NET Object From Constructor” on page 11-7.

To call method `methodName`:

```
returnedValue = methodName(classObj, args, ...)
```

### What Classes Are in a .NET Assembly?

The product documentation for your assembly contains information about its classes. However, you can use the `NET.addAssembly` command to read basic information about an assembly.

For example, to view the class names of the `mscorlib` library, type:

```
asm = NET.addAssembly('mscorlib');  
asm.Classes
```



This assembly has hundreds of entries. You can open a window to the online document for the `System` namespace reference page on the Microsoft Developer Network. For information about using this documentation, see “To Learn More About the .NET Framework” on page 11-21.

## Using the delete Function on a .NET Object

Objects created from .NET classes appear in MATLAB as reference types, or handle objects. Calling the `delete` function on a .NET handle releases all references to that .NET object from MATLAB, but does not invoke any .NET finalizers. The .NET Framework manages garbage collection.

For more information about managing handle objects in MATLAB, see “Handle Class Destructor”.

### More About

- “Properties”
- “Methods”
- “Events and Delegates”
- “Role of Classes in MATLAB”
- “Operations on Objects”

## Build a .NET Application for MATLAB Examples

You can use C# code examples in MATLAB, such as the `NetDocCell` assembly provided in “Convert .NET Arrays to Cell Arrays” on page 11-61. Build an application using a C# development tool, like Microsoft Visual Studio and then load it into MATLAB using the `NET.addAssembly` function. The following are basic steps for building; consult your development tool documentation for specific instructions.

- 1** From your development tool, open a new project and create a C# class library.
- 2** Copy the classes and other constructs from the C# files into your project.
- 3** Build the project as a DLL.
- 4** The name of this assembly is the namespace. Note the full path to the DLL file. Since it is a private assembly, you must use the full path to load it in MATLAB.
- 5** After you load the assembly, if you modify and rebuild it, you must restart MATLAB to access the new assembly. You cannot unload an assembly in MATLAB.

## Troubleshooting Security Policy Settings from Network Drives

If you run a .NET command on a MATLAB session started from a network drive, you could see a warning message. To resolve this problem, run the `enableNETfromNetworkDrive` function.

This file adds the following entry to the security policy on your machine to trust the `dotnetcli` assembly, which is the MATLAB interface to .NET module:

- Creates a group named `MathWorks_Zone` with `LocalIntranet` permission.
- Creates a `dotnetcli` subgroup within `MathWorks_Zone`.
- Provides `Full-Trust` to the `dotnetcli.dll` strong name for access to the local intranet.

You must have administrative privileges to change your configuration.

## .NET Terminology

A *namespace* is a way to group identifiers. A namespace can contain other namespaces. In MATLAB, a namespace is a package. In MATLAB, a .NET type is a class.

The syntax `namespace.ClassName` is known as a *fully qualified name*.

### .NET Framework System Namespace

`System` is the root namespace for fundamental types in the .NET Framework. This namespace also contains classes (for example, `System.String` and `System.Array`) and second-level namespaces (for example, `System.Collections.Generic`). The `microsoft` and `system` assemblies, which MATLAB loads at startup, contain many, but not all `System` namespaces. For example, to use classes in the `System.Xml` namespace, load the `system.xml` assembly using the `NET.addAssembly` command. Refer to the Microsoft .NET Framework Class Library Reference to learn what assembly to use for a specific namespace.

### Reference Type Versus Value Type

Objects created from .NET classes (for example, the `System.Reflection.Assembly` class) appear in MATLAB as *reference types*, or handle objects. Objects created from .NET structures (for example, the `System.DateTime` structure) appear as *value types*. You use the same MATLAB syntax to create and access members of classes and structures.

However, handle objects are different from value objects. When you copy a handle object, only the handle is copied and both the old and new handles refer to the same data. When you copy a value object, the object data is also copied and the new object is independent of changes to the original object. For more information about these differences, see “Copying Objects”.

Do not confuse an object created from a .NET structure with a MATLAB structure array (see “Structures”). You cannot pass a structure array to a .NET method.

## Simplify .NET Class Names

In a MATLAB command, you can refer to any class by its fully qualified name, which includes its package name. A fully qualified name might be long, making commands and functions, such as constructors, cumbersome to edit and to read. You can refer to classes by the class name alone (without a package name) if you first import the fully qualified name into MATLAB. The `import` function adds all classes that you import to a list called the import list. You can see what classes are on that list by typing `import`, without any arguments.

For example, to eliminate the need to type `System.` before every command in the “Access a Simple .NET Class” on page 11-6 example, type:

```
import System.*  
import System.DateTime.*
```

To create the object, type:

```
netDate = DateTime.Today;
```

To use a static method, type:

```
DaysInMonth(netDate.Year,netDate.Month)
```

### See Also

`import`

## Use `import` in MATLAB Functions

If you use the `import` command in a MATLAB function, add the corresponding .NET assembly before calling the function. For example, the following function `getPrinterInfo` calls methods in the `System.Drawing` namespace.

```
function ptr = getPrinterInfo
import System.Drawing.Printing.*;
ptr = PrinterSettings;
end
```

To call the function, type:

```
NET.addAssembly('System.Drawing');
printer = getPrinterInfo;
```

Do not add the command `NET.addAssembly('System.Drawing')` to the `getPrinterInfo` function. MATLAB processes the `getPrinterInfo.m` code before executing the `NET.addAssembly` command. In that case, `PrinterSettings` is not fully qualified and MATLAB does not recognize the name.

Likewise, the scope of the `import` command is limited to the `getPrinterInfo` function. At the command line, type:

```
ptr = PrinterSettings;
```

```
Undefined function or variable 'PrinterSettings'.
```

### See Also

`import`

## Nested Classes

In MATLAB, you cannot directly instantiate a nested class but here is how to do it through reflection. The following C# code defines `InnerClass` nested in `OuterClass`:

```
namespace MyClassLibrary
{
    public class OuterClass
    {
        public class InnerClass
        {
            public String strmethod(String x)
            {
                return "from InnerClass " + x;
            }
        }
    }
}
```

If the `MyClassLibrary` assembly is in your `c:\work` folder, load the file:

```
a = NET.addAssembly('C:\Work\MyClassLibrary.dll');
a.Classes
```

```
ans =
    'MyClassLibrary.OuterClass'
    'MyClassLibrary.OuterClass+InnerClass'
```

To call `strmethod`, type:

```
t = a.AssemblyHandle.GetType('MyClassLibrary.OuterClass+InnerClass');
sa = System.Activator.CreateInstance(t);
strmethod(sa, 'hello')

ans =
from InnerClass hello
```

## Handle .NET Exceptions

MATLAB catches exceptions thrown by .NET and converts them into a `NET.NetException` object, which is derived from the `MException` class. The default display of `NetException` contains the `Message`, `Source` and `HelpLink` fields of the `System.Exception` class that caused the exception. For example:

```
try
    NET.addAssembly('C:\Work\invalidfile.dll')
catch e
    e.message
    if(isa(e,'NET.NetException'))
        e.ExceptionObject
    end
end
```

### See Also

`NET.NetException`



## Pass Numeric Arguments

### In this section...

“Call .NET Methods with Numeric Arguments” on page 11-31

“Use .NET Numeric Types in MATLAB” on page 11-31

### Call .NET Methods with Numeric Arguments

When you call a .NET method in MATLAB, MATLAB automatically converts numeric arguments into equivalent .NET types, as shown in the table in “Pass Primitive .NET Types” on page 11-47.

### Use .NET Numeric Types in MATLAB

MATLAB automatically converts numeric data returned from a .NET method into equivalent MATLAB types, as shown in the table in “.NET Type to MATLAB Type Mapping” on page 11-54.

Note that MATLAB preserves .NET arrays as the relevant `System.Array` types, for example, `System.Double[]`.

MATLAB has rules for handling integers. If you are familiar with using integer types in MATLAB, and just need a reference to the rules, see the links at the end of this topic.

The default data type in MATLAB is `double`. If the data in your applications uses the default, then you need to pay attention to the numeric outputs of your .NET applications.

For more information, see:

- “Numeric Types”
- “Valid Combinations of Unlike Classes”
- “Combining Unlike Integer Types”
- “Integers”

## Pass System.String Arguments

### In this section...

“Call .NET Methods with System.String Arguments” on page 11-32

“Use System.String in MATLAB” on page 11-32

### Call .NET Methods with System.String Arguments

If an input argument to a .NET method is `System.String`, you can pass a MATLAB character array. MATLAB automatically converts a `char` array argument into `System.String`. For example, the following code uses the `System.DateTime.Parse` method to convert a date represented by a `char` array into a `DateTime` object:

```
strDate = '01 Jul 2010 3:33:02 GMT';
convertedDate = System.DateTime.Parse(strDate);
ToShortTimeString(convertedDate)
ToLongDateString(convertedDate)
```

To view the function signature for the `System.DateTime.Parse` method, type:

```
methodsview('System.DateTime')
```

Search the list for `Parse`.

Qualifiers	Return Type	Name	Arguments
Static	System.DateTime RetVal	Parse	(System.String s)

For more information, see:

- “Pass MATLAB Character Arrays” on page 11-49
- Search the MSDN website at <http://msdn.microsoft.com/en-us/default.aspx> for the term `System.DateTime`.

### Use System.String in MATLAB

This example shows how to use a `System.String` object in a MATLAB function.

Create an object representing the current time.

```
netDate = System.DateTime.Now;  
thisTime = ToShortTimeString(netDate);  
class(thisTime)
```

```
ans =  
System.String
```

The current time, `thisTime`, is a `System.String` object.

To display `thisTime` in MATLAB, use the `char` function to convert the `System.String` object to a MATLAB character array.

```
disp(['The time is ' char(thisTime)])
```

## More About

- “How MATLAB Handles System.String” on page 11-55

## Pass System.Enum Arguments

### In this section...

“Call .NET Methods with System.Enum Arguments” on page 11-34

“Use System.Enum in MATLAB” on page 11-35

### Call .NET Methods with System.Enum Arguments

An example of an enumeration is `System.DayOfWeek`. To see how to call a .NET method with this input type, use the `GetAbbreviatedDayName` method in the `System.Globalization.DateTimeFormatInfo` class. The following code displays the abbreviation for “Thursday”.

```
% Create a DayOfWeek object
thisDay = System.DayOfWeek.Thursday;
dtformat = System.Globalization.DateTimeFormatInfo;
% Display the abbreviated name of the specified day based on the
% culture associated with the current DateTimeFormatInfo object.
dtformat.GetAbbreviatedDayName(thisDay)
```

To view the function signature for the `GetAbbreviatedDayName` method, type:

```
methodsview('System.Globalization.DateTimeFormatInfo')
```

Search the list for `GetAbbreviatedDayName`.

Return Type	Name	Arguments
System.String RetVal	GetAbbreviatedDayName	( System.Globalization.DateTimeFormatInfo this, System.DayOfWeek dayofweek)

For more information, see:

- “.NET Enumerations in MATLAB” on page 11-113
- Search the MSDN website at <http://msdn.microsoft.com/en-us/default.aspx> for the term `DateTimeFormatInfo`.

## Use System.Enum in MATLAB

In MATLAB, an enumeration is a class having a finite set of named instances. You can work with .NET enumerations using features of the MATLAB enumeration class and some features unique to the .NET Framework. Some ways to use the `System.DayOfWeek` enumeration in MATLAB:

- Display an enumeration member. For example:

```
myDay = System.DateTime.Today;
disp(myDay.DayOfWeek)
```

- Use an enumeration in comparison statements. For example:

```
myDay = System.DateTime.Today;
switch(myDay.DayOfWeek)
    case {System.DayOfWeek.Saturday, System.DayOfWeek.Sunday}
        disp('Weekend')
    otherwise
        disp('Work day')
end
```

- Perform calculations. For example, the underlying type of `DayOfWeek` is `System.Int32` which you can use to perform integer arithmetic. To display the date of the first day of the current week, type:

```
myDay = System.DateTime.Today;
dow = myDay.DayOfWeek;
startDateOfWeek = AddDays(myDay, -double(dow));
ToShortDateString(startDateOfWeek)
```

- Perform bit-wise operations. For examples, see “Creating .NET Enumeration Bit Flags” on page 11-108.

For more information, see:

- “Iterate Through a .NET Enumeration” on page 11-123
- “Use .NET Enumerations to Test for Conditions” on page 11-125
- “Use Bit Flags with .NET Enumerations” on page 11-108

## Pass System.Nullable Arguments

This example shows how to handle .NET methods with `System.Nullable` type arguments, whose underlying value type is `double`.

The example shows how to call a method with a `System.Nullable` input argument. It uses the MATLAB `plot` function to show to handle a `System.Nullable` output argument.

### Build Custom Assembly NetDocNullable

To execute the MATLAB code in this example, build the `NetDocNullable` assembly. The assembly is created with the C# code, `NetDocNullable.cs`, in the `matlabroot/extern/examples/NET/NetSample` folder. To see the code, open the file in MATLAB Editor and build the `NetDocNullable` assembly.

`NetDocNullable` defines method `SetField` which has `System.Nullable` arguments.

### SetField Function Signature

Return Type	Name	Arguments
<code>System.Nullable&lt;System*Double&gt;</code> <code>RetVal</code>	<code>SetField</code>	<code>(NetDocNullable. MyClass this, System.Nullable &lt;System*Double&gt; db)</code>

### Load NetDocNullable Assembly

The example assumes you put the assembly in your `c:\work` folder. You can modify the example to change the path, `dllPath`, of the assembly.

```
dllPath = fullfile('c:', 'work', 'NetDocNullable.dll');
asm = NET.addAssembly(dllPath);
cls = NetDocNullable.MyClass;
```

Use the `cls` variable to call `SetField`, which creates a `System.Nullable<System*Double>` value from your input.

### Pass System.Nullable Input Arguments

MATLAB automatically converts `double` and `null` values to `System.Nullable<System*Double>` objects.

Pass a **double** value.

```
field1 = SetField(cls,10)

field1 =
  System.Nullable<System*Double>
  Package: System

  Properties:
    HasValue: 1
    Value: 10
  Methods, Superclasses
```

The **HasValue** property is true (1) and the **Value** property is 10.

Pass null value, [].

```
field2 = SetField(cls,[])

field2 =
  System.Nullable<System*Double>
  Package: System

  Properties:
    HasValue: 0
  Methods, Superclasses
```

The **HasValue** property is false (0), and it has no **Value** property.

### Handle System.Nullable Output Arguments in MATLAB

Before you use a **System.Nullable** object in MATLAB, first decide how to handle null values. If you ignore null values, you might get unexpected results when you use the value in a MATLAB function.

The **System.Nullable** class provides two techniques for handling null values. To provide special handling for null values, use the **HasValue** property. To treat a null value in the same way as a **double**, use the **GetValueOrDefault** method.

Create a MATLAB function, `plotValue.m`, which detects null values and treats them differently from numeric values. The input is a **System.Nullable<System\*Double>** type. If the input is null, the function displays a message. If the input value is **double**, it creates a line graph from 0 to the value.

```
function plotValue(x)
```

```
% x is System.Nullable<System*Double> type
if (x.HasValue && isfloat(x.Value))
    plot([0 x.Value])
else
    disp('No Data')
end
```

The `plotValue` function uses the `HasValue` property of the input argument to detect null values and calls the MATLAB `plot` function using the `Value` property.

Call `plotValue` with variable `field1` to display a line graph.

```
plotValue(field1)
```

Call `plotValue` with the variable `field2`, a null value.

```
plotValue(field2)
```

```
No Data
```

If you do not need special processing for null values, use the `GetValueOrDefault` method. To display the `GetValueOrDefault` function signature, type:

```
methodsview(field1)
```

Look for the following function signature:

### GetValueOrDefault Function Signature

Return Type	Name	Arguments
double scalar RetVal	GetValueOrDefault	(System.Nullable <System*Double> this)

This method converts the input variable to `double` so you can directly call the MATLAB `plot` function:

```
myData = GetValueOrDefault(field1);
plot([0 myData+2])
```

The `GetValueOrDefault` method converts a `null` value to the default numeric value, `0`.

```
defaultData = GetValueOrDefault(field2)
defaultData =
```



0

Call `plot`:

```
plot([0 defaultData])
```

You can change the default value using the `GetValueOrDefault` method. Open the `methodsvi` window and look for the following function signature:

### GetValueOrDefault Function Signature to Change Default

Return Type	Name	Arguments
double scalar RetVal	GetValueOrDefault	(System.Nullable <System*Double> this, double scalar defaultValue)

Set the `defaultValue` input argument to a new value, `-1`, and plot the results for null value `field2`.

```
defaultData = GetValueOrDefault(field2, -1);
plot([0 defaultData])
```

### Related Examples

- “Build a .NET Application for MATLAB Examples” on page 11-24

### More About

- “Pass System.Nullable Type” on page 11-49
- “How MATLAB Handles System.Nullable” on page 11-57

### External Websites

- <http://msdn.microsoft.com/en-us/default.aspx>

## Pass Cell Arrays of .NET Data

### In this section...

“Example of Cell Arrays of .NET Data” on page 11-40

“Create a Cell Array for Each System.Object” on page 11-41

“Create MATLAB Variables from the .NET Data” on page 11-41

“Call MATLAB Functions with MATLAB Variables” on page 11-41

### Example of Cell Arrays of .NET Data

In the “Convert Nested System.Object Arrays” on page 11-61 example, the cell array `mldata` contains data from the `MyGraph.getNewData` method. By reading the class documentation in the source file, you can create the following MATLAB graph:

```
dllPath = fullfile('c:', 'work', 'NetDocCell.dll');
asm = NET.addAssembly(dllPath);
graph = NetDocCell.MyGraph;

% Create cell array containing all data
mldata = cell(graph.getNewData);

% Plot the data and label the graph
figure('Name', char(mldata{1}))
plot(double(mldata{2}(2)))
xlabel(char(mldata{2}(1)))
```

However, keeping track of data of different types and dimensions and the conversions necessary to map .NET data into MATLAB types is complicated using the cell array structure. Here are some tips for working with the contents of nested `System.Object` arrays in MATLAB. After reading data from a .NET method:

- Create cell arrays for all `System.Object` arrays.
- Convert the .NET types to MATLAB types, according to the information in “Handle Data Returned from .NET Objects” on page 11-54.
- Create MATLAB variables for each type within the cell arrays.
- Call MATLAB functions with the MATLAB variables.

## Create a Cell Array for Each System.Object

This example shows how to copy `System.Object` data into a cell array.

The following statement creates the cell array `mldata`:

```
mldata = cell(graph.getNewData)

mldata =
    [1x1 System.String]    [1x1 System.Object[]]
```

This cell array contains elements of these types.

To access the contents of the `System.Object` array, create another cell array `mldata`:

```
mldata = cell(mldata{2})

mldata =
    [1x1 System.String]    [1x1 System.Double[]]
```

This cell array contains elements of these types.

## Create MATLAB Variables from the .NET Data

Assign cell data to MATLAB variables and convert:

```
% Create descriptive variables
% Convert System.String to char
mytitle = char(mldata{1});
myxlabel = char(mldata{1});
% Convert System.Double to double
y = double(mldata{2});
```

## Call MATLAB Functions with MATLAB Variables

Create a MATLAB graph with this data:

```
% Remove the previous figure
close
% Plot the data and label the graph
figure('Name',mytitle,'NumberTitle','off')
plot(y)
```

```
xlabel(myxlabel)
```

## Pass Jagged Arrays

### In this section...

“Create System.Double .NET Jagged Array” on page 11-43

“Call .NET Method with System.String Jagged Array Arguments” on page 11-43

“Call .NET Method with Multidimensional Jagged Array Arguments” on page 11-44

### Create System.Double .NET Jagged Array

This example shows how to create a .NET jagged array of `System.Double` using the `NET.createArray` function.

Create a 3 element array.

```
jArr = NET.createArray('System.Double[]',3)
```

```
jArr =
```

```
Double[][] with properties:
```

```

    Length: 3
    LongLength: 3
    Rank: 1
    SyncRoot: [1x1 System.Double[][]]
    IsReadOnly: 0
    IsFixedSize: 1
    IsSynchronized: 0
```

You can pass `jArr` to any .NET method with an input or output argument of type `System.Double[][]`.

### Call .NET Method with System.String Jagged Array Arguments

This example shows how to create an array of MATLAB character vectors to pass to a method, `MethodStringArr`, with a `System.String[][]` input argument.

The following is the MATLAB function signature for `MethodStringArr`.

Return Type	Name	Arguments
System.String[][] RetVal	MethodStringArr	(NetPackage.StringClass this,

Return Type	Name	Arguments
		System.String[][] arr)

The MATLAB character vectors you want to pass to the method are:

```
str1 = {'this', 'is'};
str2 = 'jagged';
```

Create a variable, `netArr`, of `System.String` arrays, which contains two arrays. Using the `NET.createArray`, the `typeName` for this array is `System.String[]`, and the dimension is 2.

```
netArr = NET.createArray('System.String[]',2);
```

The arrays contain empty strings.

Create `System.String` arrays to correspond to the MATLAB character vectors, `str1` and `str2`.

```
netArr(1) = NET.createArray('System.String',2);
netArr(2) = NET.createArray('System.String',1);
```

Assign `str1` and `str2` to `netArr`.

```
netArr(1) = str1;
netArr(2,1) = str2;
```

Because `str2` is a scalar and `netArr(2)` expects an array, you must assign `str2` to the specific element `netArr(2,1)`.

Now you can pass `netArr` to the `MethodStringArr` method.

```
class(netArr)
ans =
System.String[][]
```

## Call .NET Method with Multidimensional Jagged Array Arguments

This example shows how to create a MATLAB array to pass to a method, `MethodMultiDArr`, with a multidimensional jagged array input argument of `System.Double` type.

The following is the MATLAB function signature for `MethodMultiDArr`. The input is a multidimensional jagged array that contains single dimensional elements.

Return Type	Name	Arguments
<code>System.Double[][][,]</code> RetVal	<code>MethodMultiDArr</code>	( <code>NetPackage.NumericClass</code> <code>this</code> , <code>System.Double[][][,]</code> arr)

Create a 2-by-3 array with `typeName` of `System.Double[]`.

```
arr = NET.createArray('System.Double[]',2,3);
```

The elements are empty arrays.

The MATLAB arrays you want to pass to the method are:

```
A1 = [1 2 3];
A2 = [5 6 7 8];
```

MATLAB automatically converts a numeric array to the equivalent .NET type.

```
arr(1,1) = A1;
arr(1,2) = A2;
```

Array `arr` is a `System.Double[][][,]` jagged array.

```
arr
```

```
arr =
```

```
Double[][][,] with properties:
```

```
    Length: 6
   LongLength: 6
      Rank: 2
   SyncRoot: [1x1 System.Double[][][,]]
   IsReadOnly: 0
   IsFixedSize: 1
  IsSynchronized: 0
```

Now you can pass `arr` to the `MethodMultiDArr` method.

## Convert Nested System.Object Arrays

This example shows how to use the `cell` function to convert data in nested `System.Object` arrays.

The conversion of .NET arrays to cell arrays is not recursive for a `System.Object` array contained within a `System.Object` array. Use the `cell` function to convert each `System.Object` array.

The C# example `NetDocCell.cs`, in the `matlabroot/extern/examples/NET/NetSample` folder, is used in the following example. To see the code, open the file in MATLAB Editor and build the `NetDocCell` assembly.

Set up the path to your assembly, then load the assembly.

```
dllPath = fullfile('c:', 'work', 'NetDocCell.dll');  
NET.addAssembly(dllPath);
```

Create a cell array, `mldata`.

```
graph = NetDocCell.MyGraph;  
mldata = cell(graph.getNewData)
```

```
mldata =  
    [1x1 System.String]    [1x1 System.Object[]]
```

To access the contents of the `System.Object` array, create another cell array `m1PlotData`.

```
m1PlotData = cell(mldata{2})
```

```
m1PlotData =  
    [1x1 System.String]    [1x1 System.Double[]]
```

### Related Examples

- “Pass Cell Arrays of .NET Data” on page 11-40

### More About

- “Build a .NET Application for MATLAB Examples” on page 11-24



## Pass Data to .NET Objects

When you call a .NET method or function from MATLAB, MATLAB automatically converts arguments into .NET types. MATLAB performs this conversion on each passed argument, except for arguments that are already .NET objects.

The following topics provide information about passing specific data to .NET.

In this section...
“Pass Primitive .NET Types” on page 11-47
“Pass Cell Arrays” on page 11-48
“Pass Nonprimitive .NET Objects” on page 11-49
“Pass MATLAB Character Arrays” on page 11-49
“Pass System.Nullable Type” on page 11-49
“Pass NULL Values” on page 11-50
“Unsupported MATLAB Types” on page 11-50
“Choosing Method Signatures” on page 11-50
“Example — Choosing a Method Signature” on page 11-51
“Pass Arrays” on page 11-52
“Pass MATLAB Arrays as Jagged Arrays” on page 11-53

### Pass Primitive .NET Types

The following table shows the MATLAB base types for passed arguments and the corresponding .NET types defined for input arguments. Each row shows a MATLAB type followed by the possible .NET argument matches, from left to right in order of closeness of the match.

**MATLAB Primitive Type Conversion Table**

MATLAB Type	Closest Type <----- Other Matching .NET Types -----> Least Close Type											
	Preface Each .NET Type with System.											
logical	Boolean	Byte	SByte	Int16	UInt16	Int32	UInt32	Int64	UInt64	Single	Double	Object
double	Double	Single	Decimal	Int64	UInt64	Int32	UInt32	Int16	UInt16	SByte	Byte	Object
single	Single	Double	Decimal	Object								

MATLAB Type	Closest Type <----- Other Matching .NET Types -----> Least Close Type										
	Preface Each .NET Type with System.										
int8	SByte	Int16	Int32	Int64	Single	Double	Object				
uint8	Byte	UInt16	UInt32	UInt64	Single	Double	Object				
int16	Int16	Int32	Int64	Single	Double	Object					
uint16	UInt16	UInt32	UInt64	Single	Double	Object					
int32	Int32	Int64	Single	Double	Object						
uint32	UInt32	UInt64	Single	Double	Object						
int64	Int64	Double	Object								
uint64	UInt64	Double	Object								
char	Char	String	Object								

The following primitive .NET argument types do not have direct MATLAB equivalent types. MATLAB passes these types as is:

- System.IntPtr
- System.UIntPtr
- System.Decimal
- enumerated types

### Pass Cell Arrays

You can pass a cell array to a .NET property or method expecting an array of System.Object or System.String arguments, as shown in the following table.

**MATLAB Cell Array Conversion Table**

MATLAB Type	Closest Type <--- Other Matching .NET Types ---> Least Close Type		
Cell array of character arrays	System.String[ ]	System.Object[ ]	System.Object
Cell array (not all character arrays)	System.Object[ ]	System.Object	

Elements of a cell can be any of the following supported types:

- Any non-sparse, non-complex built-in numeric type shown in the MATLAB Primitive Type Conversion Table
- `char`
- `logical`
- cell array
- .NET object

## Pass Nonprimitive .NET Objects

When calling a method that has an argument of a particular .NET class, pass an object that is an instance of that class or its derived classes. You can create such an object using the class constructor, or use an object returned by a member of the class. When a class member returns a .NET object, MATLAB leaves it as a .NET object. Use this object to interact with other class members.

## Pass MATLAB Character Arrays

MATLAB automatically converts a `char` array to a .NET `System.String` object. To pass an array of `char` arrays, create a cell array.

## Pass System.Nullable Type

You can pass any of the following to a .NET method with `System.Nullable<ValueType>` input arguments:

- Variable of the underlying `<ValueType>`
- null value, `[]`
- `System.Nullable<ValueType>` object

When you pass a MATLAB variable of type `ValueType`, MATLAB reads the signature and automatically converts your variable to a `System.Nullable<ValueType>` object. For a complete list of possible `ValueType` values accepted for `System.Nullable<ValueType>`, refer to the MATLAB Primitive Type Conversion Table.

For examples, see “Pass System.Nullable Arguments” on page 11-36.

## Pass NULL Values

MATLAB uses empty double ([]) values for reference type arguments.

## Unsupported MATLAB Types

MATLAB does not support passing the following MATLAB types to .NET methods:

- Structure arrays
- Sparse arrays
- Complex numbers

## Choosing Method Signatures

MATLAB chooses the correct .NET method signature (including constructor, static and nonstatic methods) based on the following criteria.

When your MATLAB function calls a .NET method, MATLAB:

- 1 Checks to make sure that the object (or class, for a static method) has a method by that name.
- 2 Determines whether the invocation passes the same number of arguments of at least one method with that name.
- 3 Makes sure that each passed argument can be converted to the type defined for the method.

If all the preceding conditions are satisfied, MATLAB calls the method.

In a call to an overloaded method, if there is more than one candidate, MATLAB selects the one with arguments that best fit the calling arguments, based on the MATLAB Primitive Type Conversion Table. First, MATLAB rejects all methods that have any argument types that are incompatible with the passed arguments. Among the remaining methods, MATLAB selects the one with the highest fitness value, which is the sum of the fitness values of all its arguments. The fitness value for each argument is how close the MATLAB type is to the .NET type. If two methods have the same fitness, MATLAB chooses the first one defined in the class.

For class types, MATLAB chooses the method signature based on the distance of the incoming class type to the expected .NET class type. The closer the incoming type is to the expected type, the better the match.

The rules for overloaded methods with optional arguments are described in “Determining Which Overloaded Method Is Invoked” on page 11-84.

## Example — Choosing a Method Signature

Open a `methodsvew` window for the `System.String` class and look at the entries for the `Concat` method:

```
import System.*
methodsvew('System.String')
```

The `Concat` method takes one or more arguments. If the arguments are of type `System.String`, the method concatenates the values. For example, create two strings:

```
str1 = String('hello');
str2 = String('world');
```

When you type:

```
String.Concat(str1,str2)
```

MATLAB verifies the method `Concat` exists and looks for a signature with two input arguments. The following table shows the two signatures.

Qualifiers	Return Type	Name	Arguments
Static	System.String RetVal	Concat	(System.Object arg0, System.Object arg1)
Static	System.String RetVal	Concat	(System.String str0, System.String str1)

Since `str1` and `str2` are of class `System.String`, MATLAB chooses the second signature and displays:

```
ans =
helloworld
```

If the arguments are of type `System.Object`, the method displays the string representations of the values. For example, create two `System.DateTime` objects:

```
dt = DateTime.Today;
myDate = System.DateTime(dt.Year,3,1,11,32,5);
```

When you type:

```
String.Concat(dt,myDate)
```

MATLAB chooses the following signature, since `System.DateTime` objects are derived from the `System.Object` class.

Qualifiers	Return Type	Name	Arguments
Static	System.String RetVal	Concat	(System.Object arg0, System.Object arg1)

This `Concat` method first applies the `ToString` method to the objects, then concatenates the strings. MATLAB displays information like:

```
ans =  
12/23/2008 12:00:00 AM3/1/2008 11:32:05 AM
```

## Pass Arrays

For information about passing MATLAB arrays to .NET methods, see “Use Arrays with .NET Applications” on page 11-59 and “Pass MATLAB Arrays as Jagged Arrays” on page 11-53.

### How Array Dimensions Affect Conversion

The dimension of a .NET array is the number of subscripts required to access an element of the array. To get the number of dimensions, use the `Rank` property of the .NET `System.Array` type. The dimensionality of a MATLAB array is the number of non-singleton dimensions in the array.

MATLAB matches the array dimensionality with the .NET method signature, as long as the dimensionality of the MATLAB array is lower than or equal to the expected dimensionality. For example, you can pass a scalar input to a method that expects a 2-D array.

For a MATLAB array with number of dimensions, `N`, if the .NET array has fewer than `N` dimensions, the MATLAB conversion drops singleton dimensions, starting with the first one, until the number of remaining dimensions matches the number of dimensions in the .NET array.

## Converting a MATLAB Array to System.Object

You can pass a MATLAB array to a method that expects a `System.Object`.

## Pass MATLAB Arrays as Jagged Arrays

A MATLAB array is a rectangular array. The .NET Framework supports a *jagged array*, which is an array of arrays. So the elements of a jagged array can be of different dimensions and sizes.

Although .NET languages support jagged arrays, the term **jagged** is not a language keyword. C# function signatures use multiple pairs of square brackets (`[ ][ ]`) to represent a jagged array. In addition, a jagged array can be nested (`[ ][ ][ ]`), multidimensional (`[ , ]`), or nested with multidimensional elements (for example, `[ , , ] [ , ][ ]`).

MATLAB automatically converts MATLAB arrays of numeric types to the corresponding jagged array type. If the input argument is a non-numeric type or multidimensional, use the `NET.createArray` function to create an array to pass as a jagged array. For examples using `NET.createArray`, see “Pass Jagged Arrays” on page 11-43.

## Handle Data Returned from .NET Objects

### In this section...

“.NET Type to MATLAB Type Mapping” on page 11-54

“How MATLAB Handles System.String” on page 11-55

“How MATLAB Handles System.\_\_ComObject” on page 11-56

“How MATLAB Handles System.Nullable” on page 11-57

“How MATLAB Handles dynamic Type” on page 11-58

“How MATLAB Handles Jagged Arrays” on page 11-58

### .NET Type to MATLAB Type Mapping

The following table shows how MATLAB converts data from a .NET object into MATLAB types. These values are displayed in a method signature.

<b>C# .NET Type</b>	<b>MATLAB Type</b>
System.Int16	int16 scalar
System.UInt16	uint16 scalar
System.Int32	int32 scalar
System.UInt32	uint32 scalar
System.Int64	int64 scalar
System.UInt64	uint64 scalar
System.Single	single scalar
System.Double	double scalar
System.Boolean	logical scalar
System.Byte	uint8 scalar
System.Enum	enum
System.Char	char
System.Decimal	System.Decimal
System.Object	System.Object



C# .NET Type	MATLAB Type
System.IntPtr	System.IntPtr
System.UIntPtr	System.UIntPtr
System.String	System.String
System.Nullable<ValueType>	System.Nullable<ValueType>
System.Array	See “Use Arrays with .NET Applications” on page 11-59
System.__ComObject	See “How MATLAB Handles System.__ComObject” on page 11-56
<i>class name</i>	<i>class name</i>
<i>struct name</i>	<i>struct name</i>

## How MATLAB Handles System.String

Use the `char` function to convert a `System.String` object to a MATLAB character array. For example, type:

```
str = System.String('create a System.String');
strml = char(str);
whos
```

```

Name          Size          Bytes  Class

str           1x1             60  System.String
strml        1x22            44   char
```

MATLAB displays the string value of `System.String` objects, instead of the standard object display. For example, type:

```
a = System.String('test')
b = String.Concat(a, ' hello', ' world')

a =
test
b =
test hello world
```

The `System.String` class illustrates how MATLAB handles fields and properties, as described in “Call .NET Properties That Take an Argument” on page 11-86. To see

reference information about the class, search for the term `System.String` in the .NET Framework Class Library, as described in “To Learn More About the .NET Framework” on page 11-21.

## How MATLAB Handles `System.__ComObject`

The `System.__ComObject` type represents a Microsoft COM object. It is a non-visible, public class in the `mscorlib` assembly with no public methods. Under certain circumstances, a .NET object returns an instance of `System.__ComObject`. MATLAB handles the `System.__ComObject` based on the return types defined in the metadata.

### MATLAB Converts Object

If the return type of a method or property is strongly typed, and the result of the invocation is `System.__ComObject`, MATLAB automatically converts the returned object to the appropriate type.

For example, suppose that your assembly defines a type, `TestType`, and provides a method, `GetTestType`, with the following signature.

Return Type	Name	Arguments
<code>NetDocTest.TestType</code> <code>RetVal</code>	<code>GetTestType</code>	<code>(NetDocTest.MyClass this)</code>

The return type of `GetTestType` is strongly typed and the .NET Framework returns an object of type `System.__ComObject`. MATLAB automatically converts the object to the appropriate type, `NetDocTest.TestType`, shown in the following **pseudo-code**:

```
cls = NetDocTest.MyClass;
var = GetTestType(cls)

var =

    TestType handle with no properties.
```

### Casting Object to Appropriate Type

If the return type of a method or property is `System.Object`, and the result of the invocation is `System.__ComObject`, MATLAB returns `System.__ComObject`. To

use the returned object, cast it to a valid class or interface type. Use your product documentation to identify the valid types for this object.

To call a member of the new type, cast the object using the MATLAB conversion syntax:

```
objConverted = namespace.className(obj)
```

where `obj` is a `System.__ComObject` type.

For example, an item in a Microsoft Excel sheet collection can be a chart or a worksheet. The following command converts the `System.__ComObject` variable `mySheet` to a `Chart` or a `Worksheet` object `newSheet`:

```
newSheet = Microsoft.Office.Interop.Excel.interfacename(mySheet);
```

where `interfacename` is `Chart` or `Worksheet`. For an example, see “Work with Microsoft Excel Spreadsheets Using .NET” on page 11-13.

### Pass a COM Object Between Processes

If you pass a COM object to or from a function, lock the object so that MATLAB does not automatically release it when the object goes out of scope. To lock the object, call the `NET.disableAutoRelease` function. Then unlock the object, using the `NET.enableAutoRelease` function, after you are through using it.

## How MATLAB Handles System.Nullable

If .NET returns a `System.Nullable` type, MATLAB returns the corresponding `System.Nullable` type.

A `System.Nullable` type lets you assign null values to types, such as numeric types, that do not support null value. To use a `System.Nullable` object in MATLAB, first decide how to handle null values.

- If you want to process null values differently from `<ValueType>` values, use the `HasValue` property.
- If you want every value to be of the underlying `<ValueType>`, use the `GetValueOrDefault` method. This method assigns a default value of type `<ValueType>` to null values.

Use a variable of the object's underlying type where appropriate in any MATLAB expression. For examples, see “Pass System.Nullable Arguments” on page 11-36.

## How MATLAB Handles dynamic Type

MATLAB handles dynamic types as `System.Object`. For example, the following C# method `exampleMethod` has a dynamic input argument `d` and returns a dynamic output value:

```
public dynamic exampleMethod(dynamic d)
```

The following table shows the corresponding MATLAB function signature.

Return Type	Name	Arguments
<code>System.Object</code> <code>RetVal</code>	<code>exampleMethod</code>	<code>(namespace.classname this, System.Object d)</code>

## How MATLAB Handles Jagged Arrays

You must convert a .NET jagged array before using it in a MATLAB command. To convert:

- If the shape of the array is rectangular, use the corresponding MATLAB numeric function.
- If the array is not rectangular, use the `cell` function.

If the jagged array is multidimensional, you must individually convert the arrays in each dimension.

## Use Arrays with .NET Applications

### In this section...

“Passing MATLAB Arrays to .NET” on page 11-59

“Accessing .NET Array Elements in MATLAB” on page 11-59

“Converting .NET Jagged Arrays to MATLAB Arrays” on page 11-60

### Passing MATLAB Arrays to .NET

MATLAB automatically converts arrays to .NET types, as described in the MATLAB Primitive Type Conversion Table. To pass an array of character arrays, create a cell array. For all other types, use the MATLAB NET.`createArray` function.

MATLAB creates a .NET array, copies the elements from the MATLAB array to the .NET array, and passes it to C#.

### Accessing .NET Array Elements in MATLAB

You access elements of a .NET array with subscripts, just like with MATLAB arrays.

You cannot refer to the elements of a multidimensional .NET array with a single subscript (linear indexing) like you can in MATLAB, as described in “Matrix Indexing”. You must specify the index for each dimension of the .NET array.

You can only use scalar indexing to access elements of a .NET array. The colon operator, described in “Generating a Numeric Sequence”, is not supported.

### Using the Get and Set Instance Functions

Alternatively, you can access elements of a .NET array using the `Set` and `Get` instance functions. When using `Set` or `Get` you must use C# array indexing, which is zero-based.

For example, create two `System.String` arrays, using the `Set` function and direct assignment:

```
d1 = NET.createArray('System.String',3);
d1.Set(0, 'one');
d1.Set(1, 'two');
d1.Set(2, 'three');
```

```
d2 = NET.createArray('System.String',3);  
d2(1) = 'one';  
d2(2) = 'two';  
d2(3) = 'zero';
```

To compare the values of the first elements in each array, type:

```
System.String.Compare(d1(1),d2.Get(0))
```

MATLAB displays 0, meaning the strings are equal.

## Converting .NET Jagged Arrays to MATLAB Arrays

You must convert a .NET jagged array before using it in a MATLAB command.

- If the shape of the array is rectangular, use the corresponding MATLAB numeric function.
- If the array is not rectangular, use the `cell` function.

If the jagged array is multidimensional, you must individually convert the arrays in each dimension.

### See Also

`cell` | `NET.createArray`

### More About

- “Convert .NET Arrays to Cell Arrays” on page 11-61
- “Limitations to Support of .NET Arrays” on page 11-64

## Convert .NET Arrays to Cell Arrays

### In this section...

“Convert Nested System.Object Arrays” on page 11-61

“cell Function Syntax for System.Object[,] Arrays” on page 11-62

To convert .NET `System.String` and `System.Object` arrays to MATLAB cell arrays, use the `cell` function. Elements of the cell array are of the MATLAB type closest to the .NET type. For more information, see “.NET Type to MATLAB Type Mapping” on page 11-54.

For example, use the .NET Framework `System.IO.Directory` class to create a cell array of folder names in your `C:\` folder.

```
myList = cell(System.IO.Directory.GetDirectories('c:\'));
```

### Convert Nested System.Object Arrays

The conversion is not recursive for a `System.Object` array contained within a `System.Object` array. You must use the `cell` function to convert each `System.Object` array.

For an example, build the `NetDocCell` assembly using the directions in “Build a .NET Application for MATLAB Examples” on page 11-24. The source code is here.

#### C# NetDocCell Source File

```
using System;
/*
 * C# Assembly used in MATLAB .NET documentaion.
 * Method getNewData is used to demonstrate
 * how MATLAB handles a System.Object
 * that includes another System.Object.
 */
namespace NetDocCell
{
    public class MyGraph
    {
        public Object[] getNewData()
        /*
         * Create a System.Object array to use in MATLAB examples.
         */
    }
}
```

```
* Returns containerArr System.Object array containing:  
* fLabel System.String object  
* plotData System.Object array containing:  
*   xLabel System.String object  
*   doubleArr System.Double array  
*/  
{  
    String fLabel = "Figure Showing New Graph Data";  
    Double[] doubleArr = {  
18, 32, 3.133, 44, -9.9, -13, 33.03 };  
    String xLabel = "X-Axis Label";  
    Object[] plotData = { xLabel, doubleArr };  
    Object[] containerArr = { fLabel, plotData };  
    return containerArr;  
}  
}
```

Load the assembly and create a cell array, `mldata`.

```
dllPath = fullfile('c:', 'work', 'NetDocCell.dll');  
NET.addAssembly(dllPath);  
obj = NetDocCell.MyGraph;  
mldata = cell(obj.getNewData)
```

The cell array contains elements of type

```
mldata =  
    [1x1 System.String]    [1x1 System.Object[]]
```

To access the contents of the `System.Object` array, create another cell array `mldataPlotData`.

```
mldataPlotData = cell(mldata{2})
```

This cell array contains elements of type

```
mldataPlotData =  
    [1x1 System.String]    [1x1 System.Double[]]
```

## cell Function Syntax for System.Object[, ] Arrays

Use this `cell` function syntax to convert `System.DateTime` and `System.String` data to cell arrays of MATLAB data,



```
A = cell(obj, 'ConvertTypes', type)
```

where `obj` is a .NET `System.Object[, ]` array, and `type` is one of the following strings:

- `{ 'System.DateTime' }` — Convert `System.DateTime` elements to MATLAB `datetime` elements.
- `{ 'System.String' }` — Convert `System.String` elements to MATLAB character arrays.
- `{ 'all' }` — Convert all supported .NET types to equivalent MATLAB types.

`A` is a cell array, that is the same size as the `obj` array.

### Related Examples

- “Pass Cell Arrays of .NET Data” on page 11-40
- “Read Cell Arrays of Excel Spreadsheet Data” on page 11-4

## Limitations to Support of .NET Arrays

MATLAB does not support:

- Arrays which specify a lower bound
- Concatenating .NET objects into an array
- The `end` function as the last index in a .NET array
- Array indices of complex values
- Autoconversion of `char` or `cell` arrays to jagged array arguments.
- Autoconversion of MATLAB arrays to multidimensional jagged array arguments.

## Set Static .NET Properties

### In this section...

“System.Environment.CurrentDirectory Example” on page 11-65

“Do Not Use ClassName.PropertyName Syntax for Static Properties” on page 11-65

### System.Environment.CurrentDirectory Example

This example shows how to set a static property using the `NET.setStaticProperty` function.

The `CurrentDirectory` property in the `System.Environment` class is a static, read/write property. The following code creates a folder, `temp`, in the current folder and changes the `CurrentDirectory` property to the new folder.

Set your current folder to a specific path, for example:

```
cd('C:\Work')
```

Set the `CurrentDirectory` property:

```
saveDir = System.Environment.CurrentDirectory;  
newDir = [char(saveDir) '\temp'];  
mkdir(newDir)  
NET.setStaticProperty('System.Environment.CurrentDirectory',newDir)  
System.Environment.CurrentDirectory
```

```
ans =  
C:\Work\temp
```

To restore the original `CurrentDirectory` value, type:

```
NET.setStaticProperty('System.Environment.CurrentDirectory',saveDir)
```

### Do Not Use ClassName.PropertyName Syntax for Static Properties

This example shows how to mistakenly create a `struct` array instead of setting a class property.

If you use the `ClassName.PropertyName` syntax to set a static property, MATLAB creates a `struct` array.

The following code creates a structure named `System`:

```
saveDir = System.Environment.CurrentDirectory;
newDir = [char(saveDir) '\\temp'];
System.Environment.CurrentDirectory = newDir;
whos
```

Name	Size	Bytes	Class
System	1x1	376	struct
newDir	1x12	24	char
saveDir	1x1	112	System.String

Try to use a member of the `System` namespace.

```
oldDate = System.DateTime(1992,3,1);
```

```
Reference to non-existent field 'DateTime'.
```

To restore your environment, type:

```
clear System
NET.setStaticProperty('System.Environment.CurrentDirectory',saveDir)
```

## Using .NET Properties

### In this section...

“How MATLAB Represents .NET Properties” on page 11-67

“How MATLAB Maps C# Property and Field Access Modifiers” on page 11-67

### How MATLAB Represents .NET Properties

To view property names, use the `properties` function.

To get and set the value of a class property, use the MATLAB dot notation:

```
x = ClassName.PropertyName;  
ClassName.PropertyName = y;
```

The following example gets the value of a property (the current day of the month):

```
dtnow = System.DateTime.Now;  
d = dtnow.Day;
```

The following example sets the value of a property (the `Volume` for a `SpeechSynthesizer` object):

```
NET.addAssembly('System.Speech');  
ss = System.Speech.Synthesis.SpeechSynthesizer;  
ss.Volume = 50;  
Speak(ss, 'You can use .NET Libraries in MATLAB')
```

To set a static property, call the `NET.setStaticProperty` function. For an example, see “Set Static .NET Properties” on page 11-65.

MATLAB represents public .NET fields as properties.

MATLAB represents .NET properties that take an argument as methods. For more information, see “Call .NET Properties That Take an Argument” on page 11-86.

### How MATLAB Maps C# Property and Field Access Modifiers

MATLAB maps C# keywords to MATLAB property attributes, as shown in the following table.

<b>C# Property Keyword</b>	<b>MATLAB Attribute</b>
public, static	Access = public
protected, private, internal	Not visible to MATLAB
get, set	Access = public
Get	GetAccess = public, SetAccess = private
Set	SetAccess = public, GetAccess = private

MATLAB maps C# keywords to MATLAB field attributes, as shown in the following table.

<b>C# Field Keyword</b>	<b>MATLAB Mapping</b>
public	Supported
protected, private, internal, protected internal	Not visible to MATLAB

For more information about MATLAB properties, see “Property Attributes”.

## MATLAB Does Not Display Protected Properties

The `System.Windows.Media.ContainerVisual` class, available in .NET Framework Version 3.0 and above, has several protected properties. MATLAB only displays public properties and fields. Type:

```
NET.addAssembly('PresentationCore');  
properties('System.Windows.Media.ContainerVisual')
```

### Display Public Properties

Properties for class `System.Windows.Media.ContainerVisual`:

```
Children  
Parent  
Clip  
Opacity  
OpacityMask  
CacheMode  
BitmapEffect  
BitmapEffectInput  
Effect  
XSnappingGuidelines  
YSnappingGuidelines  
ContentBounds  
Transform  
Offset  
DescendantBounds  
DependencyObjectType  
IsSealed  
Dispatcher
```

To see how MATLAB handles property and field C# keywords, see “How MATLAB Maps C# Property and Field Access Modifiers” on page 11-67.

## Work with .NET Methods Having Multiple Signatures

To create the `NetSample` assembly, see “Build a .NET Application for MATLAB Examples” on page 11-24.

The `SampleMethodSignature` class defines the three constructors shown in the following table.

Return Type	Name	Arguments
<code>netdoc.SampleMethodSignature obj</code>	<code>SampleMethodSignature</code>	
<code>netdoc.SampleMethodSignature obj</code>	<code>SampleMethodSignature</code>	<code>(double scalar d)</code>
<code>netdoc.SampleMethodSignature obj</code>	<code>SampleMethodSignature</code>	<code>(System.String s)</code>

### SampleMethodSignature Class

```
using System;
namespace netdoc
{
    public class SampleMethodSignature
    {
        public SampleMethodSignature ()
        {}

        public SampleMethodSignature (double d)
        { myDoubleField = d; }

        public SampleMethodSignature (string s)
        { myStringField = s; }

        public int myMethod(string strIn, ref double dbRef,
out double dbOut)
        {
            dbRef += dbRef;
            dbOut = 65;
            return 42;
        }

        private Double myDoubleField = 5.5;
    }
}
```



```
        private String myStringField = "hello";  
    }  
}
```

## Display Function Signature Example

If you have not already loaded the `NetSample` assembly, type:

```
NET.addAssembly('c:\work\NetSample.dll')
```

Create a `SampleMethodSignature` object `obj`:

```
obj = netdoc.SampleMethodSignature;
```

To see the method signatures, type:

```
methods(obj, '-full')
```

Look for the following signatures in the MATLAB output:

```
netdoc.SampleMethodSignature obj SampleMethodSignature  
netdoc.SampleMethodSignature obj SampleMethodSignature(double scalar d)  
netdoc.SampleMethodSignature obj SampleMethodSignature(System.String s)
```

For more information about argument types, see “Handle Data Returned from .NET Objects” on page 11-54.

## Call .NET Methods With out Keyword

This example shows how to call methods that use an `out` keyword in the argument list.

The output argument `db2` in the following `outTest` method is modified by the `out` keyword.

```
using System;
namespace netdoc
{
    public class SampleOutTest
    {
        //test out keyword
        public void outTest(double db1, out double db2)
        {
            db1 = db1 * 2.35;
            db2 = db1;
        }
    }
}
```

The function signature in MATLAB is:

Return Type	Name	Arguments
double scalar db2	outTest	(netdoc.SampleOutTest this, double scalar db1)

Create an assembly from the `SampleOutTest` code, using instructions in [Build a .NET Application for MATLAB Examples](#).

Create an `asmpath` variable set to the full path to the DLL file, `SampleOutTest.dll`, created by your development tool. For example:

```
asmpath = 'c:\work\Visual Studio 2012\Projects\SampleOutTest\SampleOutTest\bin\Debug\';
asmname = 'SampleOutTest.dll';
```

Load the assembly.

```
asm = NET.addAssembly(fullfile(asmpath,asmname));
```

Call the method.

```
cls = netdoc.SampleOutTest;
```

```
db3 = outTest(cls,6)
```

```
db3 =  
    14.1000
```

## **Related Examples**

- “Build a .NET Application for MATLAB Examples” on page 11-24

## **More About**

- “C# Method Access Modifiers” on page 11-81

## Call .NET Methods With ref Keyword

This example shows how to call methods that use a `ref` keyword in the argument list.

The input argument `db1` in the following `refTest` method is modified by the `ref` keyword.

```
using System;
namespace netdoc
{
    public class SampleRefTest
    {
        //test ref keyword
        public void refTest(ref double db1)
        {
            db1 = db1 * 2;
        }
    }
}
```

The function signature in MATLAB is:

Return Type	Name	Arguments
double scalar db1	refTest	(netdoc.SampleRefTest this, double scalar db1)

Create an assembly from the `SampleRefTest` code, using instructions in Build a .NET Application for MATLAB Examples.

Create an `asmpath` variable set to the full path to the DLL file, `SampleRefTest.dll`, created by your development tool. For example:

```
asmpath = 'c:\work\Visual Studio 2012\Projects\SampleRefTest\SampleRefTest\bin\Debug\';
asmname = 'SampleRefTest.dll';
```

Load the assembly.

```
asm = NET.addAssembly(fullfile(asmpath,asmname));
```

Call the method.

```
cls = netdoc.SampleRefTest;
db4 = refTest(cls,6)
```

```
db4 =  
    12
```

## **Related Examples**

- “Build a .NET Application for MATLAB Examples” on page 11-24

## **More About**

- “C# Method Access Modifiers” on page 11-81

## Call .NET Methods With params Keyword

This example shows how to call methods that use a `params` keyword in the argument list.

The input argument `num` in the following `paramsTest` method is modified by the `params` keyword.

```
using System;
namespace netdoc
{
    public class SampleParamsTest
    {
        //test params keyword
        public int paramsTest(params int[] num)
        {
            int total = 0;
            foreach (int i in num)
            {
                total = total + i;
            }
            return total;
        }
    }
}
```

The function signature in MATLAB is:

Return Type	Name	Arguments
int32 scalar RetVal	paramsTest	(netdoc.SampleParamsTest this, System.Int32[] num)

Create an assembly from the `SampleParamsTest` code, using instructions in Build a .NET Application for MATLAB Examples.

Create an `asmpath` variable set to the full path to the DLL file, `SampleParamsTest.dll`, created by your development tool. For example:

```
asmpath = 'c:\work\Visual Studio 2012\Projects\SampleParamsTest\SampleParamsTest\bin\Debug\SampleParamsTest.dll';
asmname = 'SampleParamsTest.dll';
```

Load the assembly.

```
asm = NET.addAssembly(fullfile(asmpath,asmname));
```

Call the method.

```
cls = netdoc.SampleParamsTest;  
mat = [1, 2, 3, 4, 5, 6];  
db5 = paramsTest(cls,mat)
```

```
db5 =  
      21
```

## Related Examples

- “Build a .NET Application for MATLAB Examples” on page 11-24

## More About

- “C# Method Access Modifiers” on page 11-81

## Call .NET Methods with Optional Arguments

### In this section...

“Skip Optional Arguments” on page 11-78

“Call Overloaded Methods” on page 11-79

### Skip Optional Arguments

This example shows how to use default values in optional arguments using the `Greeting` method.

#### Greeting Function Signature

Arguments `str1` and `str2` are optional.

Return Type	Name	Arguments
System.StringRetVal	Greeting	(NetDocOptional.MyClass this, int32 scalar x, optional<System.String> str1, optional<System.String> str2)

Build the C# example, `NetDocOptional.cs` in the `matlabroot/extern/examples/NET/NetSample` folder. For information about building the assembly, see “Build a .NET Application for MATLAB Examples” on page 11-24.

Load the `NetDocOptional` assembly, if it is not already loaded.

```
dllPath = fullfile('c:', 'work', 'NetDocOptional.dll');
asm = NET.addAssembly(dllPath);
cls = NetDocOptional.MyClass;
```

The example assumes that you put the assembly in your `c:\work` folder. You can modify the `fullfile` function to change the path to the assembly.

Display the default values.

```
Greeting(cls, 0)
```

```
ans =
hello world
```



Use the default value for `str1`.

```
def = System.Reflection.Missing.Value;
Greeting(cls,0,def,'Mr. Jones')

ans =
hello Mr. Jones
```

Use the default value for `str2`. You can omit the argument at the end of a parameter list.

```
Greeting(cls,0,'My')

ans =
My world
```

## Call Overloaded Methods

This example shows how to use optional arguments with an overloaded method, `calc`. To run the example, you must create and build your own assembly `DOC` defining the `calc` method in `CLASS` with the following function signatures.

### calc Function Signatures

The following table shows the signatures for `calc`, which adds the input arguments. The difference is the type of optional argument, `y`.

Return Type	Name	Arguments
single scalarRetVal	calc	(Doc.Class this, optional<int32 scalar> x, optional<single scalar> y)
double scalarRetVal	calc	(Doc.Class this, optional<int32 scalar> x, optional<double scalar> y)

Load your assembly and create `cls`.

```
cls = Doc.Class;
```

Call `calc` with explicit arguments.

```
calc(cls,3,4)
```

```
ans =  
    7
```

If you try to use the default values by omitting the parameters, MATLAB cannot determine which signature to use.

```
calc(cls)
```

Cannot choose between the following .NET method signatures due to unspecified optional arguments in the call to 'calc':

```
'Doc.Class.calc(Doc.Class this,  
optional<int32 scalar> x, optional<single scalar> y)' and  
'Doc.Class.calc(Doc.Class this,  
optional<int32 scalar> x, optional<double scalar> y)'
```

You can resolve this ambiguity by specifying enough additional optional arguments so that there is only one possible matching .NET method.

To use the default values, you must provide both arguments.

```
def = System.Reflection.Missing.Value;  
calc(cls,def,def)  
calc(cls,3,def)  
calc(cls,def,4)
```

```
ans =  
    44  
ans =  
    14  
ans =  
    37
```

# Calling .NET Methods

## In this section...

- “Calling Object Methods” on page 11-81
- “Getting Method Information” on page 11-81
- “C# Method Access Modifiers” on page 11-81
- “VB.NET Method Access Modifiers” on page 11-82
- “Reading Method Signatures” on page 11-82

## Calling Object Methods

This topic describes information specific to .NET methods. For general information about calling methods on objects in MATLAB, see “Methods and Functions”.

## Getting Method Information

Use the following MATLAB functions to view the methods of a class. You can use these functions without creating an instance of the class. These functions do not list generic methods; use your product documentation to get information on generic methods.

- `methods` — View method names
- `methods` with `'-full'` option — View method names with argument list
- `methodsview` — Graphical representation of method list

You might find the `methodsview` window easier to use as a reference guide because you do not need to scroll through the Command Window to find information. For example, open a `methodsview` window for the `System.String` class:

```
methodsview('System.String')
```

## C# Method Access Modifiers

MATLAB maps C# keywords to MATLAB method access attributes, as shown in the following table.

<b>C# Method Keyword</b>	<b>MATLAB Attribute</b>	<b>Example</b>
ref	RHS, LHS	“Call .NET Methods With ref Keyword” on page 11-74
out	LHS	“Call .NET Methods With out Keyword” on page 11-72
params	Array of particular type	“Call .NET Methods With params Keyword” on page 11-76
protected, private, internal, protected internal	Not visible to MATLAB	

## VB.NET Method Access Modifiers

MATLAB maps VB.NET keywords to MATLAB method access attributes, as shown in the following table.

<b>VB.NET Method Keyword</b>	<b>MATLAB Attribute</b>
ByRef	LHS, RHS
ByVal	RHS
Optional	Mandatory

## Reading Method Signatures

MATLAB uses the following rules to populate method signatures.

- obj is the output from the constructor.
- this is the object argument.
- RetVal is the return type of a method.
- All other arguments use the .NET metadata.

MATLAB uses the following rules to select a method signature.

- Number of inputs

- Input type
- Number of outputs

## Calling .NET Methods with Optional Arguments

MATLAB displays optional arguments in a method signature using the `optional<T>` syntax, where T is the specific type. This feature is available in .NET Framework Version 4.0 and above.

To use a default method argument, pass an instance of `System.Reflection.Missing.Value`.

### Skipping Optional Arguments

If the method is not overloaded, you are not required to fill in all optional values at the end of a parameter list. For examples, see “Skip Optional Arguments” on page 11-78.

### Determining Which Overloaded Method Is Invoked

If a .NET class has overloaded methods with optional arguments, MATLAB picks the method matching the exact number of input arguments.

If the optional arguments of the methods are different by type, number, or dimension, MATLAB first compares the types of the mandatory arguments. If the types of the mandatory arguments are different, MATLAB chooses the first overloaded method defined in the class. If the types of the mandatory arguments are the same, specify enough optional arguments so that there is only one possible matching .NET method. Otherwise, MATLAB throws an error. For examples, see “Call Overloaded Methods” on page 11-79.

### Support for ByRef Attribute in VB.NET

The rules for optional `ByRef` arguments are the same as for other method arguments, as described in “VB.NET Method Access Modifiers” on page 11-82. `ByRef` arguments on the RHS appear as optional and behave like any other optional argument.

## Calling .NET Extension Methods

Unlike C# applications, MATLAB handles an extension method as a static method of the class that defines the method. Refer to your product documentation for the namespace and class name you need to call such methods.

For information about extension methods, see the MSDN article at [http://msdn.microsoft.com/en-us/library/bb383977\(v=VS.90\).aspx](http://msdn.microsoft.com/en-us/library/bb383977(v=VS.90).aspx).

## Call .NET Properties That Take an Argument

MATLAB represents a property that takes an argument as a method. For example, the `System.String` class has two properties, `Chars` and `Length`. The `Chars` property gets the character at a specified character position in the `System.String` object. For example:

```
str = System.String('my new string');  
methods(str)
```

### Display of System.String Methods

Methods for class `System.String`:

<code>Chars</code>	<code>Normalize</code>	<code>TrimStart</code>
<code>Clone</code>	<code>PadLeft</code>	<code>addlistener</code>
<code>CompareTo</code>	<code>PadRight</code>	<code>char</code>
<code>Contains</code>	<code>Remove</code>	<code>delete</code>
<code>CopyTo</code>	<code>Replace</code>	<code>eq</code>
<code>EndsWith</code>	<code>Split</code>	<code>findobj</code>
<code>Equals</code>	<code>StartsWith</code>	<code>findprop</code>
<code>GetEnumerator</code>	<code>String</code>	<code>ge</code>
<code>GetHashCode</code>	<code>Substring</code>	<code>gt</code>
<code>GetType</code>	<code>ToCharArray</code>	<code>isvalid</code>
<code>GetTypeCode</code>	<code>ToLower</code>	<code>le</code>
<code>IndexOf</code>	<code>ToLowerInvariant</code>	<code>lt</code>
<code>IndexOfAny</code>	<code>ToString</code>	<code>ne</code>
<code>Insert</code>	<code>ToUpper</code>	<code>notify</code>
<code>IsNormalized</code>	<code>ToUpperInvariant</code>	
<code>LastIndexOf</code>	<code>Trim</code>	
<code>LastIndexOfAny</code>	<code>TrimEnd</code>	

Static methods:

<code>Compare</code>	<code>Intern</code>	<code>op_Equality</code>
<code>CompareOrdinal</code>	<code>IsInterned</code>	<code>op_Inequality</code>
<code>Concat</code>	<code>IsNullOrEmpty</code>	
<code>Copy</code>	<code>IsNullOrWhiteSpace</code>	
<code>Format</code>	<code>Join</code>	

Notice that MATLAB displays the `Chars` property as a method.

The `Chars` method has the following signature.



Return Type	Name	Arguments
char scalarRetVal	Chars	(System.String this, int32 scalar index)

To see the first character, type:

```
Chars(str,0)
```

```
ans =  
m
```

## How MATLAB Represents .NET Operators

MATLAB supports overloaded operators, such as the C# operator symbols + and \*, as shown in the following table. MATLAB implements all other overloaded operators, such as % and +=, by their static method names, `op_Modulus` and `op_AdditionAssignment`. For a complete list of operator symbols and the corresponding operator names, see [http://msdn.microsoft.com/en-us/library/2sk3x8a7\(VS.71\).aspx](http://msdn.microsoft.com/en-us/library/2sk3x8a7(VS.71).aspx) on the Microsoft Developer Network website.

C++ operator symbol	.NET operator	MATLAB methods
+ (binary)	<code>op_Addition</code>	<code>plus</code> , +
- (binary)	<code>op_Subtraction</code>	<code>minus</code> , -
* (binary)	<code>op_Multiply</code>	<code>mtimes</code> , *
/	<code>op_Division</code>	<code>mrdivide</code> , /
&&	<code>op_LogicalAnd</code>	<code>and</code> , &
	<code>op_LogicalOr</code>	<code>or</code> ,
==	<code>op_Equality</code>	<code>eq</code> , ==
>	<code>op_GreaterThan</code>	<code>gt</code> , >
<	<code>op_LessThan</code>	<code>lt</code> , <
!=	<code>op_Inequality</code>	<code>ne</code> , ~=
>=	<code>op_GreaterThanOrEqual</code>	<code>ge</code> , >=
<=	<code>op_LessThanOrEqual</code>	<code>le</code> , <=
- (unary)	<code>op_UnaryNegation</code>	<code>uminus</code> , -a
+ (unary)	<code>op_UnaryPlus</code>	<code>uplus</code> , +a

## Limitations to Support of .NET Methods

The `methods` and `methodsview` functions do not list generic methods.

### Overloading MATLAB Functions

If your application implements a method with the same name as a MATLAB function, the method must have the same signature as the MATLAB function. Otherwise, MATLAB throws an error. For information about how MATLAB handles overloaded functions, see the following topics:

- “Overload Functions in Class Definitions”
- “Methods That Modify Default Behavior”

## Use .NET Events in MATLAB

These examples use the `addlistener` function to handle .NET events with MATLAB callbacks.

### In this section...

“Monitor Changes to .TXT File” on page 11-90

“Monitor Changes to Windows Form ComboBox” on page 11-90

### Monitor Changes to .TXT File

This example uses the `System.IO.FileSystemWatcher` class in the `System` assembly to monitor changes to a .TXT file in the `C:\work\temp` folder. Create the following event handler, `eventhandlerChanged.m`:

```
function eventhandlerChanged(source, arg)
disp('TXT file changed')
end
```

Create a `FileSystemWatcher` object `fileObj` and watch the `Changed` event for files with a `.txt` extension in the folder `C:\work\temp`.

```
file = System.IO.FileSystemWatcher('c:\work\temp');
file.Filter = '*.txt';
file.EnableRaisingEvents = true;
addlistener(file, 'Changed', @eventhandlerChanged);
```

If you modify and save a `.txt` file in the `C:\work\temp` folder, MATLAB displays:

```
TXT file changed
```

The `FileSystemWatcher` documentation says that a simple file operation can raise multiple events.

To turn off the event handler, type:

```
file.EnableRaisingEvents = false;
```

### Monitor Changes to Windows Form ComboBox

This example shows how to listen for changes to values in a `ComboBox` on a Windows Form. This example uses the `SelectedValueChanged` event defined by the `System.Windows.Forms.ComboBox` class.

To create this example, you must build a Windows Forms Application using a supported version of Microsoft Visual Studio.

- Search the Microsoft MSDN website for information about Windows Forms Applications. For example, [http://msdn.microsoft.com/en-US/library/ms235634\(v=vs.80\).aspx](http://msdn.microsoft.com/en-US/library/ms235634(v=vs.80).aspx).
- For an up-to-date list of supported compilers, see the Supported and Compatible Compilers website.

Create a 64-bit Windows Forms Application, `myForm`, in your `C:\work` folder. Add a `ComboBox` control to `Form1`, and then add one or more items to `ComboBox1`. Build the application.

To add a listener to the `form` property, create the following MATLAB class, `EnterComboData`, which uses the `attachListener` method.

```
classdef EnterComboData < handle
properties
    form
end
methods
    function x = EnterComboData
        NET.addAssembly('C:\work\myForm\myForm\bin\x64\Debug\myForm.exe');
        x.form = myForm.Form1;
        Show(x.form)
        Activate(x.form)
    end
    function r = attachListener(x)
        % create listener
        r = addlistener(
            x.form.Controls.Item(0),
            'SelectedValueChanged',
            @x.anyChange);
    end
    function anyChange(~,~,~)
        % listener action if comboBox changes
        disp('Field updated')
    end
end
end
```

To execute the following MATLAB commands, you must create and load the application named `myForm.exe`. To create a form and call its `attachListener` method, use the `EnterComboData` class.

```
form = EnterComboData;  
form.attachListener;
```

To trigger an event, select an item from the drop-down menu on the ComboBox.  
MATLAB displays:

```
Field updated
```

### **See Also**

`addlistener`

### **More About**

- “Limitations to Support of .NET Events” on page 11-106

## Call .NET Delegates in MATLAB

This example shows you how to use a delegate in MATLAB. It creates a delegate using a MATLAB function (`char`).

This example consists of the following tasks:

### In this section...

“Declare a Delegate in a C# Assembly” on page 11-93

“Load the Assembly Containing the Delegate into MATLAB” on page 11-93

“Select a MATLAB Function” on page 11-93

“Create an Instance of the Delegate in MATLAB” on page 11-94

“Invoke the Delegate Instance in MATLAB” on page 11-94

### Declare a Delegate in a C# Assembly

The C# example `NetDocDelegate.cs`, in the `matlabroot/extern/examples/NET/NetSample` folder, defines delegates used in the following examples. To see the code, open the file in MATLAB Editor. To run the examples, build the `NetDocDelegate` assembly as described in “Build a .NET Application for MATLAB Examples” on page 11-24.

### Load the Assembly Containing the Delegate into MATLAB

If the `NetDocDelegate` assembly is in your `c:\work` folder, load the file with the command:

```
dllPath = fullfile('c:', 'work', 'NetDocDelegate.dll');  
NET.addAssembly(dllPath);
```

### Select a MATLAB Function

The `delInteger` delegate encapsulates any method that takes an integer input and returns a string. The MATLAB `char` function, which converts a nonnegative integer into a character array, has a signature that matches the `delInteger` delegate. For example, the following command displays the `!` character:

```
char(33)
```

## Create an Instance of the Delegate in MATLAB

To create an instance of the `delInteger` delegate, pass the function handle of the `char` function:

```
myFunction = NetDocDelegate.delInteger(@char);
```

## Invoke the Delegate Instance in MATLAB

Use `myFunction` the same as you would `char`. For example, the following command displays the `!` character:

```
myFunction(33)
```

## See Also

`char`

## Related Examples

- “Build a .NET Application for MATLAB Examples” on page 11-24
- “Create Delegates from .NET Object Methods” on page 11-95

## More About

- “Limitations to Support of .NET Delegates” on page 11-107
- “.NET Delegates” on page 11-101



## Create Delegates from .NET Object Methods

The following C# class defines the methods `AddEggs` and `AddFlour`, which have signatures matching the `delInteger` delegate:

### C# Recipe Source File

```
using System;
namespace Recipe
{
    public class MyClass
    {
        public string AddEggs(double n)
        {
            return "Add " + n + " eggs";
        }

        public string AddFlour(double n)
        {
            return "Add " + n + " cups flour";
        }
    }
}
```

Build the `Recipe` assembly, and then load it and create a delegate `myFunc` using `AddEggs` as the callback:

```
NET.addAssembly(dllPath);
NET.addAssembly('c:\work\Recipe.dll');
myRec = Recipe.MyClass;
myFunc = NetDocDelegate.delInteger(@myRec.AddEggs);
myFunc(2)

ans =
Add 2 eggs
```

### Related Examples

- “Build a .NET Application for MATLAB Examples” on page 11-24
- “Call .NET Delegates in MATLAB” on page 11-93

### More About

- “Limitations to Support of .NET Delegates” on page 11-107

## Create Delegate Instances Bound to .NET Methods

For a C# delegate defined as:

```
namespace MyNamespace
{
    public delegate void MyDelegate();
}
```

MATLAB creates the following constructor signature.

Return Type	Name	Arguments
MyNamespace.MyDelegate obj	MyDelegate	(target, string methodName)

The argument `target` is one of the following:

- An instance of the invocation target object when binding to the instance method
- A string with fully qualified .NET class name when binding to a static method

`methodName` is a string specifying the callback method name.

### Example — Create a Delegate Instance Associated with a .NET Object Instance Method

For the following C# delegate and class definition:

```
namespace MyNamespace
{
    public delegate void MyDelegate();

    public class MyClass
    {
        public void MyMethod(){}
    }
}
```

To instantiate the delegate in MATLAB, type:

```
target = MyNamespace.MyClass();
delegate = MyNamespace.MyDelegate(target, 'MyMethod');
```

## Example — Create a Delegate Instance Associated with a Static .NET Method

For the following C# delegate and class definition:

```
namespace MyNamespace
{
    public delegate void MyDelegate();

    public class MyClass
    {
        public static void MyStaticMethod(){}
    }
}
```

To instantiate the delegate in MATLAB, type:

```
delegate = MyNamespace.MyDelegate('MyNamespace.MyClass', 'MyStaticMethod');
```

### Related Examples

- “Build a .NET Application for MATLAB Examples” on page 11-24

## .NET Delegates With `out` and `ref` Type Arguments

The MATLAB rules for mapping `out` and `ref` types for delegates are the same as for methods.

For example, the following C# statement declares a delegate with a `ref` argument:

```
public delegate void delref(ref Double refArg);
```

The signature for an equivalent MATLAB delegate function maps `refArg` as both RHS and LHS arguments:

```
function refArg = myFunc(refArg)
```

The following C# statement declares a delegate with an `out` argument:

```
public delegate void delout(  
    Single argIn,  
    out Single argOut);
```

The signature for an equivalent MATLAB delegate function maps `argOut` as an LHS argument:

```
function argOut = myFunc(argIn)
```

### More About

- “C# Method Access Modifiers” on page 11-81

## Combine and Remove .NET Delegates

MATLAB provides the instance method `Combine`, that lets you combine a series of delegates into a single delegate. The `Remove` and `RemoveAll` methods delete individual delegates. For more information, refer to the .NET Framework Class Library, as described in “To Learn More About the .NET Framework” on page 11-21.

For example, create the following MATLAB functions to use with the `NetDocDelegate.delInteger` delegate:

```
function out = action1(n)
out = 'Add flour';
disp(out)
end
```

```
function out = action2(n)
out = 'Add eggs';
disp(out)
end
```

Create delegates `step1` and `step2`:

```
step1 = NetDocDelegate.delInteger(@action1);
step2 = NetDocDelegate.delInteger(@action2);
```

To combine into a new delegate, `mixItems`, type:

```
mixItems = step1.Combine(step2);
```

Or, type:

```
mixItems = step1.Combine(@action2);
```

Invoke `mixItems`:

```
result = mixItems(1);
```

In this case, the function `action2` follows `action1`:

```
Add flour
Add eggs
```

The value of `result` is the output from the final delegate (`step2`).

```
result =  
Add eggs
```

You also can use the `System.Delegate` class static methods, `Combine`, `Remove`, and `RemoveAll`.

To remove a `step1` from `mixItems`, type:

```
step3 = mixItems.Remove(step1);
```

### See Also

[Combine](#) | [Remove](#) | [RemoveAll](#)

### Related Examples

- “Call .NET Delegates in MATLAB” on page 11-93

## .NET Delegates

In the .NET Framework, a *delegate* is a type that defines a method signature. It lets you pass a function as a parameter. The use of delegates enables .NET applications to make calls into MATLAB callback functions or class instance methods. For the rules MATLAB uses to define the signature of a callback function or class method, see “Reading Method Signatures” on page 11-82. For a complete description of delegates and when to use them, consult an outside resource, such as the Microsoft Developer Network.

There are three steps to using delegates:

- Declaration — Your .NET application contains the declaration. You cannot declare a delegate in the MATLAB language.
- Instantiation — In MATLAB, create an instance of the delegate and associate it with a specific MATLAB function or .NET object method.
- Invocation — Call the function with specified input and output arguments. Use the delegate name in place of the function name.

### Related Examples

- “Call .NET Delegates in MATLAB” on page 11-93

## Calling .NET Methods Asynchronously

### In this section...

“How MATLAB Handles Asynchronous Method Calls in .NET” on page 11-102

“Calling a Method Asynchronously Using a Callback When an Asynchronous Call Finishes” on page 11-102

“Calling a Method Asynchronously Without a Callback” on page 11-104

“Using EndInvoke With out and ref Type Arguments” on page 11-105

“Using Polling to Detect When Asynchronous Call Finishes” on page 11-105

### How MATLAB Handles Asynchronous Method Calls in .NET

It is possible to call a synchronous method asynchronously in MATLAB. With some modifications, you can use the Microsoft `BeginInvoke` and `EndInvoke` methods. For more information, refer to the MSDN article “Calling Synchronous Methods Asynchronously” at <http://msdn.microsoft.com>.

You can use delegates to call a synchronous method asynchronously by using the `BeginInvoke` and `EndInvoke` methods. If the thread that initiates the asynchronous call does not need to be the thread that processes the results, you can execute a callback method when the call completes. For information about using a callback method, see “Calling a Method Asynchronously Using a Callback When an Asynchronous Call Finishes” on page 11-102.

---

**Note:** MATLAB is a single-threaded application. Therefore, handling asynchronous calls in the MATLAB environment might result in deadlocks.

---

### Calling a Method Asynchronously Using a Callback When an Asynchronous Call Finishes

You can execute a callback method when an asynchronous call completes. A callback method executes on a different thread than the thread that processes the results of the asynchronous call.



The following is an overview of the procedure. If you do not use a callback function, follow the procedure in “Calling a Method Asynchronously Without a Callback” on page 11-104.

- Select or create a MATLAB function to execute asynchronously.
- Select or create a C# delegate and associate it with the MATLAB function.
- Create a MATLAB callback function with a System.AsyncCallback Delegate delegate signature. The signature, shown at the MSDN website, is:

```
public delegate void AsyncCallback(IAsyncResult ar)
```

- 1 Using MATLAB code, initiate the asynchronous call using the `BeginInvoke` method, specifying the callback delegate and, if required, object parameters.
- 2 Continue executing commands in MATLAB.
- 3 When the asynchronous function completes, MATLAB calls the callback function, which executes the `EndInvoke` method to retrieve the results.

### Callback Example

In this example, create the following MATLAB function to execute asynchronously:

```
function X = DivideFunction(A, B)
if B ~= 0
    X = A / B;
else
    errid = 'MyID:DivideFunction:DivisionByZero';
    error(errid, 'Division by 0 not allowed.')
end
end
```

Create the following MATLAB function, which executes as the callback when the asynchronous method invocation completes. This function displays the `result` value of the `EndInvoke` method.

```
function myCallback(asyncRes)
result = asyncRes.AsyncDelegate.EndInvoke(asyncRes);
disp(result)
end
```

Use the `del2Integer` delegate, defined in the `NetDocDelegate` assembly:

```
public delegate Int32 del2Integer(Int32 arg1, Int32 arg2);
```

Run the example:

```
% Create the delegate
divDel = NetDocDelegate.del2Integer(@DivideFunction);
A = 10;
B = 5;
% Initiate the asynchronous call.
asyncRes = divDel.BeginInvoke(A,B,@myCallback,[]);
```

MATLAB displays the result: 2

## Calling a Method Asynchronously Without a Callback

The following is an overview of the procedure. If you want to use a callback function, follow the procedure in “Calling a Method Asynchronously Using a Callback When an Asynchronous Call Finishes” on page 11-102.

- Select or create a MATLAB function to execute asynchronously.
  - Select or create a C# delegate and associate it with the MATLAB function.
- 1 In MATLAB, initiate the asynchronous call using the `BeginInvoke` method.
  - 2 Continue executing commands in MATLAB.
  - 3 Poll for asynchronous call completion using the MATLAB `pause` function.
  - 4 When the asynchronous function completes, call the `EndInvoke` method to retrieve the results.

### Example Without Callback

In this example, create the following MATLAB function, `myFunction`:

```
% MATLAB function to execute asynchronously
function res = myFunction(strValue)
res = strValue;
end
```

Use the `delString` delegate, defined in the `NetDocDelegate` assembly:

```
public delegate string delString(string message);
```

In MATLAB, create the delegate, `myDelegate`, define the input values, and start the asynchronous call:

```
myDelegate = NetDocDelegate.delString(@myFunction);  
A = 'Hello';  
asyncRes = myDelegate.BeginInvoke(A,[],[]);
```

The `BeginInvoke` method returns the object, `asyncRes`, which you use to monitor the progress of the asynchronous call. Poll for results, using the MATLAB `pause` function to let MATLAB process the events:

```
while asyncRes.IsCompleted ~= true  
    pause(0.01)  
end
```

Retrieve and display the results of the asynchronous call:

```
result = myDelegate.EndInvoke(asyncRes);  
disp(result)
```

```
Hello
```

## Using EndInvoke With out and ref Type Arguments

The MATLAB delegate signature for `EndInvoke` follows special mapping rules if your delegate has `out` or `ref` type arguments. For information about the mapping, see “.NET Delegates With out and ref Type Arguments” on page 11-98. For examples, see the `EndInvoke` reference page.

## Using Polling to Detect When Asynchronous Call Finishes

For MATLAB to process the event that executes the delegate callback on the main thread, call the MATLAB `pause` (or a similar) function.

### See Also

[BeginInvoke](#) | [EndInvoke](#)

### External Websites

- MSDN article “Calling Synchronous Methods Asynchronously”

## Limitations to Support of .NET Events

### **MATLAB Support of Standard Signature of an Event Handler Delegate**

An event handler in C# is a delegate with the following signature:

```
public delegate void MyEventHandler(object sender, MyEventArgs e)
```

The argument `sender` specifies the object that fired the event. The argument `e` holds data that can be used in the event handler. The class `MyEventArgs` is derived from the .NET Framework class `EventArgs`. MATLAB only handles events with this standard signature.

## Limitations to Support of .NET Delegates

MATLAB does not support associating a delegate instance with a generic .NET method.

When calling a method asynchronously, use the technique described in “Calling a Method Asynchronously Without a Callback” on page 11-104. Be aware that:

- MATLAB is a single-threaded application. Therefore, handling asynchronous calls in the MATLAB environment might result in deadlocks.
- For the technique described in the MSDN topic Blocking Application Execution Using an AsyncWaitHandle, MATLAB does not support the use of the `WaitOne()` method overload with no arguments.
- You cannot call `EndInvoke` to wait for the asynchronous call to complete.

## Use Bit Flags with .NET Enumerations

### In this section...

“How MATLAB Supports Bit-Wise Operations on `System.Enum`” on page 11-108

“Creating .NET Enumeration Bit Flags” on page 11-108

“Removing a Flag from a Variable” on page 11-109

“Replacing a Flag in a Variable” on page 11-109

“Testing for Membership” on page 11-110

### How MATLAB Supports Bit-Wise Operations on `System.Enum`

Many .NET languages support bit-wise operations on enumerations defined with the `System.Flags` attribute. The MATLAB language does not have equivalent operations, and, therefore, provides instance methods for performing bit-wise operations on an enumeration object. The bit-wise methods are `bitand`, `bitnot`, `bitor`, and `bitxor`.

An enumeration can define a *bit flag*. A bit flag lets you create instances of an enumeration to store combinations of values defined by the members. For example, files and folders have attributes, such as `Archive`, `Hidden`, and `ReadOnly`. For a given file, perform an operation based on one or more of these attributes. With bit-wise operators, you can create and test for combinations.

To use bit-wise operators, the enumeration must have:

- The `Flags` attribute. In Framework Version 4, these enumerations also have the `HasFlag` method.
- Values that correspond to powers of 2.

### Creating .NET Enumeration Bit Flags

Use the MATLAB example, `NetDocEnum.MyDays` enumeration, in the following examples.

Suppose that you have the following scheduled activities:

- Monday — Department meeting at 10:00
- Wednesday and Friday — Team meeting at 2:00
- Thursday — Volley ball night

You can combine members of the `MyDays` enumeration to create MATLAB variables using the `bitor` method, which joins two members. For example, to create a variable `teamMtgs` of team meeting days, type:

```
teamMtgs = bitor(...  
    NetDocEnum.MyDays.Friday,...  
    NetDocEnum.MyDays.Wednesday);
```

Create a variable `allMtgs` of all days with meetings:

```
allMtgs = bitor(teamMtgs,...  
    NetDocEnum.MyDays.Monday);
```

To see which days belong to each variable, type:

```
teamMtgs  
allMtgs  
  
teamMtgs =  
Wednesday, Friday  
  
allMtgs =  
Monday, Wednesday, Friday
```

## Removing a Flag from a Variable

Suppose that your manager cancels the Wednesday meeting this week. To remove Wednesday from the `allMtgs` variable, use the `bitxor` method.

```
thisWeekMtgs = bitxor(allMtgs,NetDocEnum.MyDays.Wednesday)  
  
thisWeekMtgs =  
Monday, Friday
```

Using a bit-wise method such as `bitxor` on `allMtgs` does not modify the value of `allMtgs`. This example creates a variable, `thisWeekMtgs`, which contains the result of the operation.

## Replacing a Flag in a Variable

Suppose that you change the team meeting permanently from Wednesday to Thursday. To remove Wednesday, use `bitxor`, and use `bitor` to add Thursday. Since this is a permanent change, update the `teamMtgs` and `allMtgs` variables.

```
teamMtgs = bitor(...
```

```
        (bitand(teamMtgs,...
                bitnot(NetDocEnum.MyDays.Wednesday))),...
        NetDocEnum.MyDays.Thursday);
allMtgs = bitor(teamMtgs,...
                NetDocEnum.MyDays.Monday);
teamMtgs
allMtgs

teamMtgs =
Thursday, Friday

allMtgs =
Monday, Thursday, Friday
```

## Testing for Membership

Create the following RemindMe function:

```
function RemindMe(day)
% day = NetDocEnum.MyDays enumeration
teamMtgs = bitor(...
            NetDocEnum.MyDays.Friday,...
            NetDocEnum.MyDays.Wednesday);
allMtgs = bitor(teamMtgs,...
                NetDocEnum.MyDays.Monday);

if eq(day,bitand(day,teamMtgs))
    disp('Team meeting today.')
elseif eq(day,bitand(day,allMtgs))
    disp('Meeting today.')
else
    disp('No meetings today!')
end
end
```

Use the RemindMe function:

```
today = NetDocEnum.MyDays.Monday;
RemindMe(today)

Meeting today.
```

## See Also

bitand | bitnot | bitor | bitxor



## **Related Examples**

- “NetDocEnum Example Assembly” on page 11-116

## Read Special System Folder Path

```
function result = getSpecialFolder(arg)
% Returns the special system folders such as "Desktop", "MyMusic" etc.
% arg can be any one of the enum element mentioned in this link
% http://msdn.microsoft.com/en-us/library/
% system.environment.specialfolder.aspx
% e.g.
%     >> getSpecialFolder('Desktop')
%
%     ans =
%     C:\Users\jsmith\Desktop

% Get the type of SpecialFolder enum, this is a nested enum type.
specialFolderType = System.Type.GetType(...
    'System.Environment+SpecialFolder');
% Get a list of all SpecialFolder enum values
folders = System.Enum.GetValues(specialFolderType);
enumArg = [];

% Find the matching enum value requested by the user
for i = 1:folders.Length
    if (strcmp(char(folders(i)), arg))
        enumArg = folders(i);
        break
    end
end

% Validate
if isempty(enumArg)
    error('Invalid Argument')
end

% Call GetFolderPath method and return the result
result = System.Environment.GetFolderPath(enumArg);
end
```

### Related Examples

- “Iterate Through a .NET Enumeration” on page 11-123

## .NET Enumerations in MATLAB

MATLAB allows you to work with *.NET enumerations* using features of the MATLAB enumeration class and some features unique to the .NET Framework.

Terms you should know:

- Enumeration — In MATLAB, a class having a finite set of named instances.
- Enumeration member — Named instance of an enumeration class.
- Underlying value — Numeric value associated with an enumeration member.

Enumerations contain the following information:

- Members
- Methods
- Underlying Values

In this topic, the term **enumeration** refers to a .NET enumeration.

---

**Note:** The MATLAB language supports user-defined enumeration classes. If you are using enumerations defined in MATLAB, refer to the topics under Enumerations.

---

## Default Methods for an Enumeration

By default, MATLAB provides the following methods for a .NET enumeration:

- Relational operators — `eq`, `ne`, `ge`, `gt`, `le`, and `lt`.
- Conversion methods — `char`, `double`, and a method to get the underlying value.
- Bit-wise methods — Only for enumerations with the `System.Flags` attribute.

For example, type:

```
methods('System.DayOfWeek')
```

```
Methods for class System.DayOfWeek:
```

```
CompareTo      eq
DayOfWeek      ge
Equals         gt
GetHashCode    int32
GetType        le
GetTypeCode    lt
ToString       ne
char
double
```

The method to get the underlying value is `int32`.

The `NetDocEnum.MyDays` enumeration, which has the `Flags` attribute, has the bit-wise methods. To list the methods, type:

```
methods('NetDocEnum.MyDays')
```

```
Methods for class NetDocEnum.MyDays:
```

```
CompareTo      char
Equals         double
GetHashCode    eq
GetType        ge
GetTypeCode    gt
MyDays         int32
ToString       le
bitand         lt
bitnot         ne
bitor
```

bitxor

## **Related Examples**

- “Using Relational Operations” on page 11-125
- “Using Switch Statements” on page 11-125
- “Display .NET Enumeration Members as Character Vectors” on page 11-121
- “NetDocEnum Example Assembly” on page 11-116

## **More About**

- “Use Bit Flags with .NET Enumerations” on page 11-108

## NetDocEnum Example Assembly

The C# example `NetDocEnum.cs`, in the `matlabroot/extern/examples/NET/NetSample` folder, defines enumerations used in examples. To see the code, open the file in MATLAB Editor. To run the examples, build the `NetDocEnum` assembly as described in “Build a .NET Application for MATLAB Examples” on page 11-24.

If the `NetDocEnum` assembly is in your `c:\work` folder, load the file:

```
dllPath = fullfile('c:', 'work', 'NetDocEnum.dll');
asm = NET.addAssembly(dllPath);
asm.Enums

ans =
    'NetDocEnum.MyDays'
    'NetDocEnum.Range'
```

## Work with Members of a .NET Enumeration

To display the member names of an enumeration, use the MATLAB enumeration function. For example, to list the member names of the `System.DayOfWeek` enumeration, type:

```
enumeration('System.DayOfWeek')

Enumeration members for class 'System.DayOfWeek':
    Sunday
    Monday
    Tuesday
    Wednesday
    Thursday
    Friday
    Saturday
```

You cannot use the `enumeration` command to return arrays of .NET enumeration objects. You can read the names and values of the enumeration into arrays, using the `System.Enum` methods `GetNames`, `GetValues`, and `GetType`.

For example, to create arrays `allNames` and `allValues` for the `System.DayOfWeek` enumeration, type:

```
myDay = System.DayOfWeek;
allNames = System.Enum.GetNames(myDay.GetType);
allValues = System.Enum.GetValues(myDay.GetType);
```

The class of the names array is `System.String`, while the class of the values array is the enumeration type `System.DayOfWeek`.

```
whos all*

    Name      Size  Bytes  Class
    allNames  1x1   112   System.String[]
    allValues  1x1   112   System.DayOfWeek[]
```

Although the types are different, the information MATLAB displays is the same. For example, type:

```
allNames(1)

ans =
```

Sunday

Type:

allValues(1)

ans =  
Sunday

### See Also

enumeration

### Related Examples

- “Iterate Through a .NET Enumeration” on page 11-123

### More About

- “Information About System.Enum Methods” on page 11-123
- “How MATLAB Handles System.String” on page 11-55



## Refer to a .NET Enumeration Member

You use an *enumeration member* in your code as an instance of an enumeration. To refer to an enumeration member, use the C# namespace, enumeration, and member names:

```
Namespace . EnumName . MemberName
```

For example, the `System` namespace in the .NET Framework class library has a `DayOfWeek` enumeration. The members of this enumeration are:

```
Enumeration members for class 'System.DayOfWeek':
    Sunday
    Monday
    Tuesday
    Wednesday
    Thursday
    Friday
    Saturday
```

To create a variable with the value `Thursday`, type:

```
gameDay = System.DayOfWeek.Thursday;
whos
```

Name	Size	Bytes	Class
gameDay	1x1	104	System.DayOfWeek

## Using the Implicit Constructor

The implicit constructor, *Namespace.EnumName*, creates a member with the default value of the underlying type. For example, the `NetDocEnum.Range` enumeration has the following members:

```
Enumeration members for class 'NetDocEnum.Range':
    Max
    Min
```

Type:

```
x = NetDocEnum.Range
whos x
x =
```

0

Name	Size	Bytes	Class
x	1x1	104	NetDocEnum.Range

### Related Examples

- “NetDocEnum Example Assembly” on page 11-116

## Display .NET Enumeration Members as Character Vectors

To get the descriptive name of an enumeration, use the `char` method. For example, type:

```
gameDay = System.DayOfWeek.Thursday;  
[ 'Next volleyball game is ',char(gameDay) ]
```

```
ans =  
Next volleyball game is Thursday
```

## Convert .NET Enumeration Values to Type Double

To convert a value to a MATLAB double, type:

```
gameDay = System.DayOfWeek.Thursday;  
myValue = double(gameDay)
```

```
myValue =  
    4
```

## Iterate Through a .NET Enumeration

### In this section...

“Information About System.Enum Methods” on page 11-123

“Display Enumeration Member Names” on page 11-124

### Information About System.Enum Methods

To create MATLAB arrays from an enumeration, use the static `System.Enum` methods `GetNames` and `GetValues`. The input argument for these methods is an enumeration type. Use the `GetType` method for the type of the current instance. To display the signatures for these methods, type:

```
methodsview('System.Enum')
```

Look at the following signatures:

Qualifiers	Return Type	Name	Arguments
	<code>System.Type</code>	<code>GetType</code>	<code>(System.Enum this)</code>
Static	<code>System.String[]</code>	<code>GetNames</code>	<code>(System.Type enumType)</code>
Static	<code>System.Array</code>	<code>GetValues</code>	<code>(System.Type enumType)</code>

To use `GetType`, create an instance of the enumeration. For example:

```
myEnum = System.DayOfWeek;
```

The `enumType` for `myEnum` is:

```
myEnumType = myEnum.GetType;
```

To create an array of names using the `GetNames` method, type:

```
allNames = System.Enum.GetNames(myEnumType);
```

Alternatively:

```
allNames = System.Enum.GetNames(myEnum.GetType);
```

## Display Enumeration Member Names

To display all member names of the `System.DayOfWeek` enumeration, create a `System.String` array of names. Use the `Length` property of this array to find the number of members. For example:

```
myDay = System.DayOfWeek;  
allNames = System.Enum.GetNames(myDay.GetType);  
disp(['Members of ' class(myDay)])  
for idx = 1:allNames.Length  
    disp(allNames(idx))  
end
```

```
Members of System.DayOfWeek  
Sunday  
Monday  
Tuesday  
Wednesday  
Thursday  
Friday  
Saturday
```

## Related Examples

- “Read Special System Folder Path” on page 11-112

## Use .NET Enumerations to Test for Conditions

### In this section...

“Using Switch Statements” on page 11-125

“Using Relational Operations” on page 11-125

With relational operators, you can use enumeration members in `if` and `switch` statements and other functions that test for equality.

### Using Switch Statements

The following `Reminder` function displays a message depending on the day of the week:

```
function Reminder(day)
% day = System.DayOfWeek enumeration value
% Add error checking here
switch(day)
    case System.DayOfWeek.Monday
        disp('Department meeting at 10:00')
    case System.DayOfWeek.Tuesday
        disp('Meeting Free Day!')
    case {System.DayOfWeek.Wednesday System.DayOfWeek.Friday}
        disp('Team meeting at 2:00')
    case System.DayOfWeek.Thursday
        disp('Volley ball night')
end
end
```

For example, type:

```
today = System.DayOfWeek.Wednesday;
Reminder(today)
```

```
ans =
Team meeting at 2:00
```

### Using Relational Operations

Create the following function to display a message:

```
function VolleyballMessage(day)
```

```
% day = System.DayOfWeek enumeration value
if gt(day, System.DayOfWeek.Thursday)
    disp('See you next week at volleyball.')
else
    disp('See you Thursday!')
end
end
```

For a day before Thursday:

```
myDay = System.DayOfWeek.Monday;
VolleyballMessage(myDay)
```

See you Thursday!

For a day after Thursday:

```
myDay = System.DayOfWeek.Friday;
VolleyballMessage(myDay)
```

See you next week at volleyball.



## Underlying Enumeration Values

MATLAB supports enumerations of any numeric type.

To find the underlying type of an enumeration, use the `System.Enum` static method `GetUnderlyingType`. For example, the following C# statement in the `NetDocEnum` assembly declares the enumeration `Range`:

```
public enum Range : long {Max = 2147483648L,Min = 255L}
```

To display the underlying type:

```
maxValue = NetDocEnum.Range.Max;  
System.Enum.GetUnderlyingType(maxValue.GetType).FullName  
  
ans =  
System.Int64
```

### Related Examples

- “NetDocEnum Example Assembly” on page 11-116

## **Limitations to Support of .NET Enumerations**

You cannot create arrays of .NET enumerations, or any .NET objects, in MATLAB.

## Create .NET Collections

This example uses two `System.String` arrays, `d1` and `d2`, to create a generic collection list. It shows how to manipulate the list and access its members. To create the arrays, type:

```
d1 = NET.createArray('System.String',3);
d1(1) = 'Brachiosaurus';
d1(2) = 'Shunosaurus';
d1(3) = 'Allosaurus';

d2 = NET.createArray('System.String',4);
d2(1) = 'Tyrannosaurus';
d2(2) = 'Spinosaurus';
d2(3) = 'Velociraptor';
d2(4) = 'Triceratops';
```

Create a generic collection, `dc`, to contain `d1`. The `System.Collections.Generic.List` class is in the `mscorlib` assembly, which MATLAB loads automatically.

```
dc = NET.createGeneric('System.Collections.Generic.List',{ 'System.String' },3)

List<System*String> handle

Capacity: 3
Count: 0
```

The `List` object `dc` has a `Capacity` of three, but currently is empty (`Count = 0`).

Use the `AddRange` method to add the contents of `d1` to the list. For more information, search the Web for `System.Collections.Generic` and select the `List` class.

```
AddRange(dc,d1);
```

List `dc` now has three items:

```
dc.Count
```

To display the contents, use the `Item` method and zero-based indexing:

```
for i = 1:dc.Count
    disp(dc.Item(i-1))
end
```

```
Brachiosaurus  
Shunosaurus  
Allosaurus
```

Another way to add values is to use the `InsertRange` method. Insert the `d2` array starting at index 1:

```
InsertRange(dc,1,d2);
```

The size of the array has grown to seven. To display the values, type:

```
for i = 1:dc.Count  
    disp(dc.Item(i-1))  
end
```

```
Brachiosaurus  
Tyrannosaurus  
Spinosaurus  
Velociraptor  
Triceratops  
Shunosaurus  
Allosaurus
```

The first item in the `d2` array ('Tyrannosaurus') is at index 1 in list `dc`:

```
System.String.Compare(d2(1),dc.Item(1))
```

The `System.String.Compare` answer, 0, indicates that the two values are equal.

### External Websites

- [.NET Framework 4.5 System.Collections.Generic.List Class](#)

## Convert .NET Collections to MATLAB Arrays

Use the `ToArray` method of the `System.Collections.Generic.List` class to convert a collection to an array. For example, use `GetRange` to get three values from the list, starting with index 2. Then call `ToArray` to create a `System.String` array `dArr`, and display the results:

```
temp = GetRange(dc,2,3);  
dArr = ToArray(temp);  
for i = 1:dArr.Length  
    disp(dArr(i))  
end
```

```
Spinosaurus  
Velociraptor  
Triceratops
```

To create a MATLAB array `D`:

```
D = {char(dArr(1)),char(dArr(2)),char(dArr(3))}  
  
D =  
    'Spinosaurus'    'Velociraptor'    'Triceratops'
```

Now you can use `D` in MATLAB functions. For example, if you type:

```
D'  
  
ans =  
    'Spinosaurus'  
    'Velociraptor'  
    'Triceratops'
```

Sort the array alphabetically:

```
sort(D)  
  
ans =  
    'Spinosaurus'    'Triceratops'    'Velociraptor'
```

## Create .NET Arrays of Generic Type

This example creates a .NET array of `List<Int32>` generic type.

```
genType = NET.GenericClass('System.Collections.Generic.List',...  
    'System.Int32');  
arr = NET.createArray(genType, 5)
```

```
arr =
```

```
List<System*Int32>[] with properties:
```

```
    Length: 5  
    LongLength: 5  
    Rank: 1  
    SyncRoot: [1x1 System.Collections.Generic.List<System*Int32>[]]  
    IsReadOnly: 0  
    IsFixedSize: 1  
    IsSynchronized: 0
```

## Display .NET Generic Methods Using Reflection

### In this section...

“showGenericMethods Function” on page 11-133

“Display Generic Methods in a Class” on page 11-134

“Display Generic Methods in a Generic Class” on page 11-135

### showGenericMethods Function

The showGenericMethods function, reads a .NET object or a fully qualified class name and returns a cell array of the names of the generic method in the given class or object. Create the following MATLAB functions:

```
function output = showGenericMethods(input)
% if input is a .NET object, get MethodInfo[]
if IsNetObject(input)
    methods = GetType.GetMethods(input);
    % if input is a string, get the type and get get MethodInfo[]
elseif ischar(input) && ~isempty(input)
    type = getType(input);
    if isempty(type)
        disp(strcat(input, ' not found'))
        return
    end
    methods = GetMethods(type);
else
    return
end
% generate generic method names from MethodInfo[]
output = populateGenericMethods(methods);
```

end

```
function output = populateGenericMethods(methods)
% generate generic method names from MethodInfo[]
index = 1;
for i = 1:methods.Length
    method = methods(i);
    if method.IsGenericMethod
        output{index,1} = method.ToString.char;
        index = index + 1;
    end
end
```

```
        end
    end
end

function result = IsNetObject(input)
% Must be sub class of System.Object to be a .NET object
result = isa(input, 'System.Object');
end

function outputType = getType(input)
% Input is a string representing the class name
% First try the static GetType method of Type handle.
% This method can find any type from
% System or mscorlib assemblies
outputType = System.Type.GetType(input, false, false);
if isempty(outputType)
    % Framework's method to get the type failed.
    % Manually look for it in
    % each assembly visible to MATLAB
    assemblies = System.AppDomain.CurrentDomain.GetAssemblies;
    for i = 1:assemblies.Length
        asm = assemblies.Get(i-1);
        % Look for a particular type in the assembly
        outputType = GetType(asm, input, false, false);
        if ~isempty(outputType)
            % Found the type - done
            break
        end
    end
end
end
end
```

## Display Generic Methods in a Class

The `NetDocGeneric` assembly contains a class with generic methods.

```
dllPath = fullfile('c:', 'work', 'NetDocGeneric.dll');
asm = NET.addAssembly(dllPath);
asm.Classes

ans =
    'NetDocGeneric.SampleClass'
```

Display the methods in `SampleClass`:



```
showGenericMethods('NetDocGeneric.SampleClass')
ans =
'K GenMethod[K](K)'
'K GenMethodWithMixedArgs[K](K, K, Boolean)'
'K GenStaticMethod[K](K)'
'K GenStaticMethodWithMixedArgs[K](K, K, Boolean)'
```

## Display Generic Methods in a Generic Class

The `NetDocGeneric` assembly contains a generic class with generic methods.

```
dllPath = fullfile('c:', 'work', 'NetDocGeneric.dll');
asm = NET.addAssembly(dllPath);
asm.GenericTypes
```

```
ans =
'NetDocGeneric.SampleGenericClass`1[T]'
```

Display the methods in `SampleGenericClass`:

```
cls = NET.createGeneric('NetDocGeneric.SampleGenericClass', {'System.Double'});
showGenericMethods(cls)
ans =
'System.String ParameterizedGenMethod[K](Double, K)'
'T GenMethod[T](T)'
'K GenStaticMethod[K](K)'
'K GenStaticMethodWithMixedArgs[K](K, K, Boolean)'
'System.String ParameterizedStaticGenMethod[K](Double, K)'
```

## .NET Generic Classes

Generics are classes and methods that have placeholders (type parameters or *parameterized types*) for one or more types. This lets you design classes that take in a generic type and determine the actual type at run time. A common use for generic classes is to work with collections. For information about generic methods, see “Call .NET Generic Methods” on page 11-138.

The `NET.createGeneric` function creates an instance of the specialized generic class given the following:

- Fully qualified name of the generic class definition
- List of fully qualified parameter type names for generic type specialization
- Variable list of constructor arguments

Use instances of the `NET.GenericClass` helper class in `NET.createGeneric` function's parameter type list when specialization requires another parameterized class definition. The class instances serve as parameterized data type definitions and are constructed using fully qualified generic type name and a variable length list of fully qualified type names for generic type specialization. This list can also contain instances of `NET.GenericClass` if an extra nested level of parameterization is required.

## Accessing Items in .NET Collections

Use the `Item` property of the `System.Collections.Generic.List` class to get or set an element at a specified index. Since `Item` is a property that takes arguments, MATLAB maps it to a pair of methods to get and set the value. For example, the syntax to use `Item` to get a value is:

Return Type	Name	Arguments
<code>System.String</code> <code>RetVal</code>	<code>Item</code>	<code>(System.Collections.Generic. List&lt;System*String&gt; this, int32 scalar index)</code>

The syntax to use `Item` to set a value is:

Return Type	Name	Arguments
<code>none</code>	<code>Item</code>	<code>(System.Collections.Generic. List&lt;System*String&gt; this, int32 scalar index, System.String value)</code>

### Related Examples

- “Create .NET Collections” on page 11-129

## Call .NET Generic Methods

A *generic method* declares one or more parameterized types. For more information, search for the term **generics** in the .NET Framework Class Library, as described in “To Learn More About the .NET Framework” on page 11-21.

Use the `NET.invokeGenericMethod` function to call a generic method. How you use the `NET.invokeGenericMethod` depends if the method is static or if it is a member of a generic class.

### In this section...

“Using the `NetDocGeneric` Example” on page 11-138

“Invoke Generic Class Member Function” on page 11-139

“Invoke Static Generic Functions” on page 11-139

“Invoke Static Generic Functions of a Generic Class” on page 11-139

“Invoke Generic Functions of a Generic Class” on page 11-140

## Using the `NetDocGeneric` Example

The C# example `NetDocGeneric.cs`, in the `matlabroot/extern/examples/NET/NetSample` folder, defines simple generic methods to illustrate the `NET.invokeGenericMethod` syntax. To see the code, open the file in MATLAB Editor. Build the `NetDocGeneric` assembly as described in “Build a .NET Application for MATLAB Examples” on page 11-24.

If you created the assembly `NetDocGeneric` and put it in your `C:\work` folder, type the following MATLAB commands to load the assembly:

```
dllPath = fullfile('c:', 'work', 'NetDocGeneric.dll');  
NET.addAssembly(dllPath);
```

---

**Note:** The `methods` and `methodsview` functions do not list generic methods. Use the “Display .NET Generic Methods Using Reflection” on page 11-133 example.

---

## Invoke Generic Class Member Function

The `GenMethod` method in `NetDocGeneric.SampleClass` returns the input argument as type `K`. To call `GenMethod`, create an object, `cls`:

```
cls = NetDocGeneric.SampleClass();
```

To convert `5` to an integer parameter type, such as `System.Int32`, call `NET.invokeGenericMethod` with the object:

```
ret = NET.invokeGenericMethod(cls, ...
    'GenMethod', ...
    {'System.Int32'}, ...
    5);
```

The `GenMethodWithMixedArgs` method has parameterized typed arguments, `arg1` and `arg2`, and a strongly-typed argument, `tf`, of type `bool`. The `tf` flag controls which argument `GenMethodWithMixedArgs` returns. To return `arg1`, use the syntax:

```
ret = NET.invokeGenericMethod(cls, 'GenMethodWithMixedArgs', ...
    {'System.Double'}, 5, 6, true);
```

To return `arg2`, use the syntax:

```
ret = NET.invokeGenericMethod(cls, 'GenMethodWithMixedArgs', ...
    {'System.Double'}, 5, 6, false);
```

## Invoke Static Generic Functions

To invoke static method `GenStaticMethod`, call `NET.invokeGenericMethod` with the fully qualified class name:

```
ret = NET.invokeGenericMethod('NetDocGeneric.SampleClass', ...
    'GenStaticMethod', ...
    {'System.Int32'}, ...
    5);
```

## Invoke Static Generic Functions of a Generic Class

If a static function is a member of a generic class, create a class definition using the `NET.GenericClass` constructor:

```
genClsDef = NET.GenericClass('NetDocGeneric.SampleGenericClass', ...
```

```
'System.Double');
```

To invoke static method `GenStaticMethod` of `SampleGenericClass`, call `NET.invokeGenericMethod` with the class definition:

```
ret = NET.invokeGenericMethod(genClsDef, ...  
    'GenStaticMethod', ...  
    {'System.Int32'}, ...  
    5);
```

## Invoke Generic Functions of a Generic Class

If a generic method uses the same parameterized type as the generic class, you can call the function directly on the class object. If the generic uses a different type than the class, use the `NET.invokeGenericMethod` function.

# Using COM Objects from MATLAB

---

- “MATLAB COM Integration” on page 12-2
- “Registering Controls and Servers” on page 12-5
- “Getting Started with COM” on page 12-7
- “Use Internet Explorer in MATLAB Figure” on page 12-10
- “Read Spreadsheet Data Using Excel as Automation Server” on page 12-15
- “Supported Client/Server Configurations” on page 12-22

## MATLAB COM Integration

In this section...
“Concepts and Terminology” on page 12-2
“COM Objects, Clients, and Servers” on page 12-2
“Interfaces” on page 12-3
“The MATLAB COM Client” on page 12-3
“The MATLAB COM Automation Server” on page 12-4

### Concepts and Terminology

While the ideas behind COM technology are straightforward, the terminology is not. The meaning of COM terms has changed over time and few concise definitions exist. Here are some terms that you should be familiar with. These are not comprehensive definitions. For a complete description of COM, you'll need to consult outside resources.

### COM Objects, Clients, and Servers

A COM *object* is a software component that conforms to the Component Object Model. COM enforces encapsulation of the object, preventing direct access of its data and implementation. COM objects expose interfaces, which consist of properties, methods and events.

A COM *client* is a program that makes use of COM objects. COM objects that expose functionality for use are called COM *servers*. COM servers can be in-process or out-of-process. An example of an out-of-process server is Microsoft Excel spreadsheet program.

A Microsoft *ActiveX*<sup>®</sup> *control* is a type of in-process COM server that requires a control container. ActiveX controls typically have a user interface. An example is the Microsoft Calendar control. A control container is an application capable of hosting ActiveX controls. A MATLAB figure window or a Simulink model are examples of control containers.

MATLAB can be used as either a COM client or a COM Automation server.



## Interfaces

The functionality of a component is defined by one or more interfaces. To use a COM component, you must learn about its interfaces, and the methods, properties, and events implemented by the component. The component vendor provides this information.

There are two standard COM interfaces:

- **IUnknown** — An interface required by all COM components. All other COM interfaces are derived from IUnknown.
- **IDispatch** — An interface that exposes objects, methods and properties to applications that support Automation.

## The MATLAB COM Client

A COM client is a program that manipulates COM objects. These objects can run in the MATLAB application or can be part of another application that exposes its objects as a programmatic interface to the application.

Using MATLAB as a COM client provides two techniques for developing programs in MATLAB:

- You can include COM components in your MATLAB application (for example, a spreadsheet).
- You can access existing applications that expose objects via Automation.

In a typical scenario, MATLAB creates ActiveX controls in figure windows, which are manipulated by MATLAB through the controls' properties, methods, and events. This is useful because there exists a wide variety of graphical user interface components implemented as ActiveX controls. For example, the Microsoft Internet Explorer<sup>®</sup> program exposes objects that you can include in a figure to display an HTML file. There also are treeviews, spreadsheets, and calendars available from a variety of sources.

MATLAB COM clients can access applications that support Automation, such as the Excel spreadsheet program. In this case, MATLAB creates an Automation server in which to run the application and returns a handle to the primary interface for the object created.

### The MATLAB COM Automation Server

*Automation* provides an infrastructure whereby applications called automation controllers can access and manipulate (i.e. set properties of or call methods on) shared automation objects that are exported by other applications, called Automation servers. Any Windows program that can be configured as an Automation controller can control MATLAB.

For example, using Microsoft Visual Basic<sup>®</sup> programming language, you can run a MATLAB script in a Microsoft PowerPoint<sup>®</sup> presentation. In this case, PowerPoint is the controller and MATLAB is the server.

### More About

- “Create COM Objects” on page 13-3
- “MATLAB COM Automation Server”

## Registering Controls and Servers

Before using COM objects, you must register their controls and servers. Most are registered by default. However, if you get a new `.ocx`, `.dll`, or other object file for the control or server, you must register the file manually in the Windows registry.

Use the Windows `regsvr32` command to register your file. From the Windows prompt, use the `cd` function to go to the folder containing the object file. If your object file is an `.ocx` file, type:

```
regsvr32 filename.ocx
```

For example, to register the MATLAB control `mwsamp2.ocx`, type:

```
cd matlabroot\toolbox\matlab\winfun\win32
regsvr32 mwsamp2.ocx
```

If you encounter problems with this procedure, consult a Windows manual or contact your local system administrator.

### Accessing COM Controls Created with .NET

If you create a COM control using Microsoft .NET Framework 4, use the DOS `regasm` command with the `/codebase` option to register your file.

### Verifying the Registration

Here are several ways to verify that a control or server is registered. These examples use the MATLAB `mwsamp` control. Refer to your Microsoft product documentation for information about using Microsoft Visual Studio or the Microsoft Registry Editor programs.

- Go to the Visual Studio .NET 2003 Tools menu and execute the ActiveX control test container. Click **Edit**, insert a new control, and select **MwSamp Control**. If you are able to insert the control without any problems, the control is successfully registered. This method only works on controls.
- Open the Registry Editor by typing `regedit` at the DOS prompt. Search for your control or server object by selecting **Find** from the **Edit** menu. It will likely be in the following structure:

```
HKEY_CLASSES_ROOT/progid
```

- Open OLEViewer from the Visual Studio .NET 2003 Tools menu. Look in the following structure for your Control object:

```
Object Classes : Grouped by Component Category : Control :  
Your_Control_Object_Name (i.e. Object Classes : Grouped by  
Component Category : Control : Mwsamp Control)
```

## Getting Started with COM

### In this section...

“Creating an Instance of a COM Object” on page 12-7

“Getting Information About a Particular COM Control” on page 12-7

“Getting an Object's ProgID” on page 12-8

“Registering a Custom Control” on page 12-8

### Creating an Instance of a COM Object

Two MATLAB functions enable you to create COM objects:

- `actxcontrol` — Creates an instance of a control in a MATLAB figure.
- `actxserver` — Creates and manipulates objects from MATLAB that are exposed in an application that supports Automation.

Each function returns a *handle* to the object's main interface, which you use to access the object's methods, properties, and events, and any other interfaces it provides.

### Getting Information About a Particular COM Control

In general, you can determine what you can do with an object using the `methods`, `get`, and `events` functions.

#### Information about Methods

To list the methods supported by the object *handle*, type:

```
methods(handle)
```

#### Information about Properties

To list the properties of the object *handle*, type:

```
get(handle)
```

To see the value of the property *PropertyName*, type:

```
get(handle, 'PropertyName')
```

Use the `set` function to change a property value.

### Information about Events

To list the events supported by the object *handle*, type:

```
events(handle)
```

### Getting an Object's ProgID

To get the programmatic identifier (ProgID) of a COM control that is already registered on your computer, use the `actxcontrol` command. You can also use the **ActiveX Control Selector**, displayed with the command `actxcontrolselect`. This interface lets you see instances of the controls installed on your computer.

### Registering a Custom Control

If your MATLAB program uses a custom control (e.g., one that you have created especially for your application), you must register it with the Microsoft Windows operating system before you can use it. You can do this from your MATLAB program by issuing an operating system command:

```
!regsvr32 /s filename.ocx
```

where *filename* is the name of the file containing the control. Using this command in your program enables you to provide custom-made controls that you make available to other users by registering the control on their computer when they run your MATLAB program. You might also want to supply versions of a Microsoft ActiveX control to ensure that all users have the same version.

### See Also

`actxcontrol` | `actxcontrol`list | `actxcontrol`select | `actxserver` | `events` | `get` | `methods` | `set`

### Related Examples

- “Creating an ActiveX Control” on page 13-4

### More About

- “Registering Controls and Servers” on page 12-5

- “COM Methods” on page 13-24
- “COM Events” on page 13-27
- “COM Object Interfaces” on page 13-32

## Use Internet Explorer in MATLAB Figure

This example uses the ActiveX control `Shell.Explorer`, which is exposed by the Microsoft Internet Explorer application, to include an HTML viewer in a MATLAB figure. The figure's window button down function is then used to select a graphics object when the user clicks the graph and load the object's property documentation into the HTML viewer.

### Techniques Demonstrated

- Using Internet Explorer from an ActiveX client program.
- Defining a window button down function that displays HTML property documentation for whatever object the user clicks.
- Defining a `resize` function for the figure that also resizes the ActiveX object container.

### Using the Figure to Access Properties


This example creates a larger than normal figure window that contains an axes object and an HTML viewer on the lower part of the figure window. By default, the viewer displays the URL `http://www.mathworks.com`. When you issue a plotting command, such as:

```
surf(c( peaks(20) )
```

the graph displays in the axes.

Click anywhere in the graph to see the property documentation for the selected object.





## Complete Code Listing

You can open the file that implements this example in MATLAB Editor or you can run this example with the following links:

- [Open file in editor](#)
- [Run this example](#)

## Creating the Figure

This example defines the figure size based on the default figure size and adds space for the ActiveX control. Here is the code to define the figure:

```
dfpos = get(0,'DefaultFigurePosition');
hfig = figure('Position',dfpos([1 2 3 4]).* [.8 .2 1 1.65],...
    'Menu','none','Name','Create a plot and click on an object',...
    'ResizeFcn',@reSize,...
    'WindowButtonDownFcn',@wbdf,...
    'Renderer','OpenGL');
```

Note that the figure also defines a resize function and a window button down function by assigning function handles to the `ResizeFcn` and `WindowButtonDownFcn` properties. The callback functions `reSize` and `wbdf` are defined as nested functions in the same file.

## Calculating the ActiveX Object Container Size

The `actxcontrol` function creates the ActiveX control inside the specified figure and returns the control's handle. You need to supply the following information:

- Control's programmatic identifier (use `actxcontrollist` to find it)
- Location and size of the control container in the figure (pixels) [left bottom width height]
- Handle of the figure that contains the control:

```
conSize = calcSize; % Calculate the container size
hExp = actxcontrol('Shell.Explorer.2',conSize,hfig); % Create the control
Navigate(hExp,'http://www.mathworks.com/'); % Specify content of html viewer
```

The nested function, `calcSize` calculates the size of the object container based on the current size of the figure. `calcSize` is also used by the figure `reSize` function, which is described in the next section.

```
function conSize = calcSize
fp = get(hfig,'Position'); % Get current figure size
conSize = [0 0 1 .45].*fp([3 4 3 4]); % Calculate container size
end % calcSize
```

## Automatic Resize

In MATLAB, you can change the size of a figure and the axes automatically resize to fit the new size. This example implements similar resizing behavior for the ActiveX object container within the figure using the object's `move` method. This method enables you to change both size and location of the ActiveX object container (i.e., it is equivalent to setting the figure `Position` property).

When you resize the figure window, the MATLAB software automatically calls the function assigned to the figure's `ResizeFcn` property. This example implements the nested function `resize` for the figure `resize` function.

### ResizeFcn at Figure Creation

The `resize` function first determines if the ActiveX object exists because the MATLAB software calls the figure `resize` function when the figure is first created. Since the ActiveX object has not been created at this point, the `resize` function simply returns.

### When the Figure Is Resized

When you change the size of the figure, the `resize` function executes and does the following:

- Calls the `calcSize` function to calculate a new size for the control container based on the new figure size.
- Calls the control's `move` method to apply the new size to the control.

### Figure `ResizeFcn`.

```
function resize(~,~)
if ~exist('hExp','var')
    return
end
conSize = calcSize;
move(hExp,conSize);
end % resize
```

## Selecting Graphics Objects

This example uses the figure `WindowButtonDownFcn` property to define a callback function that handles mouse click events within the figure. When you click the left

mouse button while the cursor is over the figure, the MATLAB software executes the `WindowButtonDownFcn` callback on the mouse down event.

The callback determines which object was clicked by querying the figure `CurrentObject` property, which contains the handle of the graphics object most recently clicked. Once you have the object's handle, you can determine its type and then load the appropriate HTML page into the `Shell.Explorer` control.

The nested function `wbdf` implements the callback. Once it determines the type of the selected object, it uses the control `Navigate` method to display the documentation for the object type.

### Figure `WindowButtonDownFcn`.

```
function wbdf(~,~)
    cobj = get(hfig,'CurrentObject');
    if isempty(cobj)
        disp('Click somewhere else')
        return
    end
    pth = 'http://www.mathworks.com/access/helpdesk/help/techdoc/ref/';
    typ = get(cobj,'Type');
    switch typ
        case ('figure')
            Navigate(hExp,[pth,'figure_props.html']);
        case ('axes')
            Navigate(hExp,[pth,'axes_props.html']);
        case ('line')
            Navigate(hExp,[pth,'line_props.html']);
        case ('image')
            Navigate(hExp,[pth,'image_props.html']);
        case ('patch')
            Navigate(hExp,[pth,'patch_props.html']);
        case ('surface')
            Navigate(hExp,[pth,'surface_props.html']);
        case ('text')
            Navigate(hExp,[pth,'text_props.html']);
        case ('hgroup')
            Navigate(hExp,[pth,'hgroupproperties.html']);
        otherwise
            Navigate(hExp,[pth(1:end-4),'infotool/hgprop/doc_frame.html']);
    end
end % wbdf
```

## Read Spreadsheet Data Using Excel as Automation Server

For alternatives to importing Excel spreadsheet data into MATLAB, see the functions and examples in “Spreadsheets”.

This example creates a user interface to access the data in a Microsoft Excel file. To enable the communication between MATLAB and the spreadsheet program, this example creates a Microsoft ActiveX object in an Automation server running an Excel application. MATLAB then accesses the data in the spreadsheet through the interfaces provided by the Excel Automation server.

### Techniques Demonstrated


- Use of an Automation server to access another application from MATLAB.
- Ways to manipulate Excel data into types used in the UI and plotting.
- Implementing a UI that enables plotting of selected columns of the Excel spreadsheet.
- Inserting a MATLAB figure into an Excel file.

### Using the UI

To use the UI, select any items in the list box and click the **Create Plot** button. The sample data provided with this example contain three input and three associated response data sets, all of which are plotted versus the first column in the Excel file, which is the time data.

You can view the Excel data file by clicking the **Show Excel Data File** button, and you can save an image of the graph in a different Excel file by clicking **Save Graph** button. Note that the **Save Graph** option creates a temporary PNG file in the current folder, if you have write-access permission.

The following picture shows the UI with an input/response pair selected in the list box and plotted in the axes.




### Complete Code Listing

You can open the file used to implement this example in MATLAB Editor or run this example:

- Open file in editor.
- Run this example.

### Excel Spreadsheet Format

This example assumes a particular organization of the Excel spreadsheet, as shown in the following picture.



	A	B	C	D	E	F	G
1	Time	InputAil	InputEle	InputRud	RespAil	RespEle	RespRud
2	0	0.00E+00	2.8827	-0.0004868	0	0	0
3	0	0.00E+00	2.8827	-0.0004868	0	0	0
4	0	0.00E+00	2.8827	-0.0004868	0	0	0
5	0.00E+00	0.00E+00	2.8827	-0.0004868	0	0.00E+00	0.00E+00
6	0.00E+00	0.00E+00	2.8827	-0.0004868	0.00E+00	0.00E+00	0.00E+00
7	0.00E+00	0.00E+00	2.8828	-0.0004868	0.00E+00	0.00E+00	0.00E+00
8	0.00E+00	0.00E+00	2.8832	-0.0004868	0.00E+00	0.00E+00	0.00E+00
9	0.00E+00	0.00E+00	2.8853	-0.0004873	0.00E+00	0.00E+00	0.00E+00
10	0.000141	0.00E+00	2.8955	-0.0004995	0.00E+00	0.00E+00	0.00E+00
11	0.000358	0	2.9154	-0.0005692	0.00E+00	0.00035612	0.00E+00
12	0.000358	0	2.9154	-0.0005692	0.00E+00	0.00035612	0.00E+00
13	0.000358	0	2.9154	-0.0005692	0.00E+00	0.00035612	0.00E+00
14	0.000876	0.00E+00	2.9628	-0.0009769	0	0.0021199	0.00E+00
15	0.000876	0.00E+00	2.9628	-0.0009769	0	0.0021199	0.00E+00
16	0.000876	0.00E+00	2.9628	-0.0009769	0	0.0021199	0.00E+00
17	0.000876	0.00E+00	2.9628	-0.0009769	0	0.0021199	0.00E+00
18	0.000876	0.00E+00	2.9628	-0.0009769	0	0.0021199	0.00E+00

The format of the Excel file is as follows:

- The first element in each column is text that identifies the data contain in the column. These values are extracted and used to populate the list box.
- The first column (Time) is used for the  $x$ -axis of all plots of the remaining data.
- All rows in each column are read into MATLAB.

## Excel Automation Server

The first step in accessing the spreadsheet data from MATLAB is to run the Excel application in an Automation server process using the `actxserver` function and the program ID, `excel.application`.

```
exl = actxserver('excel.application');
```

The ActiveX object that is returned provides access to a number of interfaces supported by the Excel program. Use the workbook interface to open the Excel file containing the data.

```
exlWkbk = exl.Workbooks;
```

```
exlFile = exlWkbk.Open([docroot ' /techdoc/matlab_external/examples/input_resp_data.xls']);
```

Use the workbook's sheet interface to access the data from a range object, which stores a reference to a range of data from the specified sheet. This example accesses all the data in column A, first cell to column G, last cell:

```
exlSheet1 = exlFile.Sheets.Item('Sheet1');  
robj = exlSheet1.Columns.End(4); % Find the end of the column  
numrows = robj.row; % And determine what row it is  
dat_range = ['A1:G' num2str(numrows)]; % Read to the last row  
rngObj = exlSheet1.Range(dat_range);
```

At this point, the entire data set from the Excel file's `sheet1` is accessed via the range object interface. This object returns the data in a MATLAB cell array, which can contain both numeric and character data:

```
exlData = rngObj.Value;
```

### Manipulating the Data in the MATLAB Workspace

Now that the data is in a cell array, you can use MATLAB functions to extract and reshape parts of the data into the forms needed to use in the UI and pass to the plot function.

The following code performs two operations:

- Extracts numeric data from the cell array (indexing with curly braces), concatenates the individual doubles returned by the indexing operation (square brackets), and reshapes it into an array that arranges the data in columns.
- Extracts the text in the first cell in each column of an Excel sheet and stores them in a cell array, which is used to generate the items in the list box.

```
for ii = 1:size(exlData,2)  
    matData(:,ii) = reshape([exlData{2:end,ii}],size(exlData(2:end,ii)));  
    listBox{ii} = [exlData{1,ii}];  
end
```

### The Plotter UI

This example uses a UI that enables you to select from a list of input and response data from a list box. All data is plotted as a function of time (which is, therefore, not a choice in the list box) and you can continue to add more data to the graph. Each data plot added to the graph causes the legend to expand.

Additional implementation details include:



- A legend that updates as you add data to a graph
- A clear button that enables you to clear all graphs from the axes
- A save button that saves the graph as a PNG file and adds it to another Excel file
- A toggle button that shows or hides the Excel file being accessed
- The figure delete function (`DeleteFcn` property), which MATLAB calls when the figure is closed, is used to terminate the Automation server process.

### Selecting and Plotting Data

When you click the **Create Plot** button, its callback function queries the list box to determine what items are selected and plots each data versus time. The legend is updated to display any new data while maintaining the legend for the existing data.

```
function plotButtonCallback(src,evnt)
iSelected = get(listBox,'Value');
grid(a,'on');hold all
for p = 1:length(iSelected)
    switch iSelected(p)
        case 1
            plot(a,tme,matData(:,2))
        case 2
            plot(a,tme,matData(:,3))
        case 3
            plot(a,tme,matData(:,4))
        case 4
            plot(a,tme,matData(:,5))
        case 5
            plot(a,tme,matData(:,6))
        case 6
            plot(a,tme,matData(:,7))
        otherwise
            disp('Select data to plot')
    end
end
end
[b,c,g,lbs] = legend([lbs lBoxList(iSelected+1)]);
end % plotButtonCallback
```

### Clearing the Axes

The plotter is designed to continually add graphs as the user selects data from the list box. The **Clear Graph** button clears and resets the axes and clears the variable used to store the labels of the plot data (used by legend).

```
%% Callback for clear button
function clearButtonCallback(src,evt)
    cla(a,'reset')
    lbs = '';
end % clearButtonCallback
```

### Display or Hide Excel File

The MATLAB program has access to the properties of the Excel application running in the Automation server. By setting the **Visible** property to 1 or 0, this callback controls the visibility of the Excel file.

```
%% Display or hide Excel file
function dispButtonCallback(src,evt)
    exl.visible = get(src,'Value');
end % dispButtonCallback
```

### Close Figure and Terminate Excel Automation Process

Since the Excel Automation server runs in a separate process from MATLAB, you must terminate this process explicitly. There is no reason to keep this process running after the UI has been closed, so this example uses the figure's delete function to terminate the Excel process with the **Quit** method. Also, terminate the second Excel process used for saving the graph. See “Inserting MATLAB Graphs Into Excel Spreadsheets” on page 12-20 for information on this second process.

```
%% Terminate Excel processes
function deleteFig(src,evt)
    exlWkbk.Close
    exlWkbk2.Close
    exl.Quit
    exl2.Quit
end % deleteFig
```

### Inserting MATLAB Graphs Into Excel Spreadsheets

You can save the graph created with this UI in an Excel file. (This example uses a separate Excel Automation server process for this purpose.) The callback for the **Save Graph** push button creates the image and adds it to an Excel file:

- Both the axes and legend are copied to an invisible figure configured to print the graph as you see it on the screen (figure `PaperPositionMode` property is set to `auto`).

- The `print` command creates the PNG image.
- Use the `Shapes` interface to insert the image in the Excel workbook.

The server and interfaces are instanced during UI initialization phase:

```
exl2 = actxserver('excel.application');
exlWkbk2 = exl2.Workbooks;
wb = invoke(exlWkbk2, 'Add');
graphSheet = invoke(wb.Sheets, 'Add');
Shapes = graphSheet.Shapes;
```

The following code implements the **Save Graph** button callback:

```
function saveButtonCallback(src,evt)
    tempfig = figure('Visible','off','PaperPositionMode','auto');
    tempfigfile = [tempname '.png'];
    ah = findobj(f,'type','axes');
    copyobj(ah,tempfig) % Copy both graph axes and legend axes
    print(tempfig, '-dpng',tempfigfile);
    Shapes.AddPicture(tempfigfile,0,1,50,18,300,235);
    exl2.visible = 1;
end
```

## See Also

`xlsread`

## More About

- “Ways to Import Spreadsheets”

## Supported Client/Server Configurations

### In this section...

“Introduction” on page 12-22

“MATLAB Client and In-Process Server” on page 12-22

“MATLAB Client and Out-of-Process Server” on page 12-23

“COM Implementations Supported by MATLAB Software” on page 12-24

“Client Application and MATLAB Automation Server” on page 12-24


“Client Application and MATLAB Engine Server” on page 12-25

### Introduction

You can configure MATLAB software to either control or be controlled by other COM components. When MATLAB controls another component, MATLAB is the client, and the other component is the server. When another component controls MATLAB, MATLAB is the server.

### MATLAB Client and In-Process Server

The following diagram shows how the MATLAB client interacts with an “In-Process Server” on page 14-5.



The server exposes its properties and methods through the IDispatch (Automation) interface or a Custom interface, depending on which interfaces the component implements. For information on accessing interfaces, see “COM Object Interfaces” on page 13-32 .

### Microsoft ActiveX Controls

An ActiveX control is an object with a user interface. When MATLAB constructs an ActiveX control, it places the control's UI in a MATLAB figure window. Click the

various options available in the user interface (e.g., making a particular menu selection) to trigger *events* that get communicated from the control in the server to the client MATLAB application. The client decides what to do about each event and responds accordingly.

MATLAB comes with a sample ActiveX control called `mwsamp`. This control draws a circle on the screen and displays some text. You can use this control to try out MATLAB COM features. For more information, see “MATLAB Sample ActiveX Control `mwsamp`” on page 13-53.

### DLL Servers

Any COM component that has been implemented as a dynamic link library (DLL) is also instantiated in an in-process server. That is, it is created in the same process as the MATLAB client application. When MATLAB uses a DLL server, it runs in a separate window rather than a MATLAB figure window.


MATLAB responds to events generated by a DLL server in the same way as events from an ActiveX control.

### For More Information

To learn more about working with MATLAB as a client, see “Create COM Objects” on page 13-3.

## MATLAB Client and Out-of-Process Server

In this configuration, a MATLAB client application interacts with a component that has been implemented as a “Local Out-of-Process Server” on page 14-5. Examples of out-of-process servers are Microsoft Excel and Microsoft Word programs.



As with in-process servers, this server exposes its properties and methods through the IDispatch (Automation) interface or a Custom interface, depending on which interfaces the component implements. For information on accessing interfaces, see “COM Object Interfaces” on page 13-32.

Since the client and server run in separate processes, you have the option of creating the server on any system on the same network as the client.

If the component provides a user interface, its window is separate from the client application.

MATLAB responds to events generated by an out-of-process server in the same way as events from an ActiveX control.

### For More Information


To learn more about working with MATLAB as a client, see “Create COM Objects” on page 13-3.

## COM Implementations Supported by MATLAB Software

MATLAB only supports COM implementations that are compatible with the Microsoft Active Template Library (ATL) API. In general, your COM object should be able to be contained in an ATL host window in order to work with MATLAB.

## Client Application and MATLAB Automation Server

MATLAB operates as the Automation server in this configuration. It can be created and controlled by any Microsoft Windows program that can be an *Automation controller*. Some examples of Automation controllers are Microsoft Excel, Microsoft Access™, Microsoft Project, and many Microsoft Visual Basic and Microsoft Visual C++ programs.



MATLAB Automation server capabilities include the ability to execute commands in the MATLAB workspace, and to get and put matrices directly from and into the workspace. You can start a MATLAB server to run in either a shared or dedicated mode. You also have the option of running it on a local or remote system.

To create the MATLAB server from an external application program, use the appropriate function from that language to instantiate the server. (For example,

use the Visual Basic `CreateObject` function.) For the programmatic identifier, specify `matlab.application`. To run MATLAB as a dedicated server, use the `matlab.application.single` programmatic identifier. See “Shared and Dedicated Servers” on page 14-4 for more information.

The function that creates the MATLAB server also returns a handle to the properties and methods available in the server through the `IDispatch` interface.

---

**Note:** Because VBScript client programs require an Automation interface to communicate with servers, this is the only configuration that supports a VBScript client.


---

### For More Information

To learn more about working with Automation servers, see “MATLAB COM Automation Server Interface” on page 14-4.

## Client Application and MATLAB Engine Server

MATLAB provides a faster custom interface called `IEngine` for client applications written in C, C++, or Fortran. MATLAB uses `IEngine` to communicate between the client application and the MATLAB engine running as a COM server.



Use the MATLAB Engine API functions to start and end the server process, and to send commands to be processed by MATLAB.

### For More Information

To learn more about the MATLAB engine and the functions provided in its C/C++ and Fortran API Reference libraries, see “MATLAB Engine API for C, C++, and Fortran”.





# MATLAB COM Client Support

---

- “Create COM Objects” on page 13-3
- “Handle COM Data in MATLAB” on page 13-12
- “COM Object Properties” on page 13-21
- “COM Methods” on page 13-24
- “COM Events” on page 13-27
- “COM Event Handlers” on page 13-29
- “COM Object Interfaces” on page 13-32
- “Save and Delete COM Objects” on page 13-35
- “MATLAB Application as DCOM Client” on page 13-37
- “Explore COM Objects” on page 13-38
- “Change Row Height in Range of Spreadsheet Cells” on page 13-42
- “Write Data to Excel Spreadsheet Using ActiveX” on page 13-44
- “Change Cursor in Spreadsheet” on page 13-46
- “Insert Spreadsheet After First Sheet” on page 13-47
- “Redraw Circle in `mwsamp` Control” on page 13-48
- “Connect to Existing Excel Application” on page 13-50
- “Display Message for Workbook `OnClose` Event” on page 13-51
- “Combine Event Handlers as MATLAB Local Functions” on page 13-52
- “MATLAB Sample ActiveX Control `mwsamp`” on page 13-53
- “Display Event Messages from `mwsamp` Control” on page 13-54
- “Add Position Property to `mwsamp` Control” on page 13-57
- “Save `mwsamp2` COM Control” on page 13-58
- “Deploy ActiveX Controls Requiring Run-Time Licenses” on page 13-59
- “Microsoft Forms 2.0 Controls” on page 13-61
- “COM Collections” on page 13-63

- “MATLAB COM Support Limitations” on page 13-64
- “Interpreting Argument Callouts in COM Error Messages” on page 13-65

## Create COM Objects


In this section...
“Creating the Server Process — An Overview” on page 13-3
“Creating an ActiveX Control” on page 13-4
“Creating a COM Server” on page 13-9

### Creating the Server Process — An Overview

MATLAB software provides two functions to create a COM object:

- `actxcontrol` — Creates a Microsoft ActiveX control in a MATLAB figure window.
- `actxserver` — Creates an in-process server for a dynamic link library (DLL) component or an out-of-process server for an executable (EXE) component.

The following diagram shows the basic steps in creating the server process. For more information on how the MATLAB software establishes interfaces to the resultant COM object, see “COM Object Interfaces” on page 13-32.



## Creating an ActiveX Control

You can create an instance of an ActiveX control from the MATLAB client using either a user interface (`actxcontrolselect`) or the `actxcontrol` function from the command line. Either of these methods creates an instance of the control in the MATLAB client process and returns a handle to the primary interface to the COM object. Through this interface, you can access the public properties or methods of the object. You can also establish more interfaces to the object, including interfaces that use `IDispatch`, and any custom interfaces that might exist.

This section describes how to create an instance of the control and how to position it in the MATLAB figure window.

- “Listing Installed Controls” on page 13-5
- “Finding a Particular Control” on page 13-5
- “Creating Control Objects Using a UI” on page 13-6
- “Creating Control Objects from the Command Line” on page 13-9
- “Repositioning the Control in a Figure Window” on page 13-9
- “Limitations to ActiveX Support” on page 13-9

### Listing Installed Controls

The `actxcontrollist` function shows you what COM controls are currently installed on your system. Type:

```
list = actxcontrollist
```

MATLAB displays a cell array listing each control, including its name, programmatic identifier (ProgID), and file name.

This example shows information for several controls (your results might be different):

```
list = actxcontrollist;  
s = sprintf(' Name = %s\n ProgID = %s\n File = %s\n', list{114:115,:})
```

MATLAB displays:

```
s =  
  
Name = OleInstall Class  
ProgID = Outlook Express Mime Editor  
File = OlePrn.OleInstall.1  
Name = OutlookExpress.MimeEdit.1  
ProgID = C:\WINNT\System32\oleprn.dll  
File = C:\WINNT\System32\inetcomm.dll
```

### Finding a Particular Control

If you know the name of a control, you can display its ProgID and the path of the folder containing it. For example, some of the examples in this documentation use the `Mwsamp2` control. You can find it with the following code:

```
list = actxcontrollist;
for ii = 1:length(list)
    if ~isempty(strfind([list{ii,:}], 'Mwsamp2'))
        s = sprintf(' Name = %s\n ProgID = %s\n File = %s\n', ...
                    list{ii,:})
    end
end

s =

Name = Mwsamp2 Control
ProgID = MWSAMP.MwsampCtrl.2
File =
D:\Apps\MATLAB\R2006a\toolbox\matlab\winfun\win32\mwsamp2.ocx
```


The location of this file depends on your MATLAB installation.

### Creating Control Objects Using a UI

Using the `actxcontrolselect` function is the simplest way to create an instance of a control object. This function displays all controls installed on your system. When you select an item from the list and click the **Create** button, MATLAB creates the control and returns a handle to it. Type:

```
h = actxcontrolselect
```

MATLAB displays the **Select an ActiveX Control** dialog box.



The interface has an **ActiveX Control List** selection pane on the left and a **Preview** pane on the right. To see a preview of the control, click one of the control names in the selection pane. (A blank preview pane means that the control does not have a preview.) If MATLAB cannot create the instance, an error message appears in the preview pane.

### Setting Properties with `actxcontrolselect`

To change property values when creating the control, click the **Properties** button in the **Preview** pane. You can select which figure window to put the control in (**Parent** field), where to position it in the window (**X** and **Y** fields), and what size to make the control (**Width** and **Height**).

You can register events you want the control to respond to in this window. Enter the name of the routine to the right of the event under **Event Handler**.

You can select callback routines by clicking a name in the **Event** column, and then clicking the **Browse** button. To assign a callback routine to more than one event, first press the **Ctrl** key and click individual event names. Alternatively, drag the mouse over consecutive event names, and then click **Browse** to select the callback routine.

MATLAB only responds to registered events, so if you do not specify a callback, the event is ignored.

For example, in the **ActiveX Control List** pane, select **Calendar Control 10.0** (the version on your system might be different) and click **Properties**. MATLAB displays the Choose ActiveX Control Creation Parameter dialog box. To change the default size for the control, enter a **Width** of 500 and a **Height** of 350. To create an instance of the Calendar control, click **OK** in this window, and click **Create** in the next window.

You can also set control parameters using the `actxcontrol` function. One parameter you can set with `actxcontrol`, but not with `actxcontrolselect`, is the name of an initialization file. When you specify this file name, MATLAB sets the initial state of the control to that of a previously saved control.

#### Information Returned by `actxcontrolselect`

The `actxcontrolselect` function creates an object that is an instance of the MATLAB COM class. The function returns up to two arguments: a handle for the object, `h`, and a 1-by-3 cell array, `info`, containing information about the control. To get this information, type:

```
[h, info] = actxcontrolselect
```

The cell array `info` shows the name, ProgID, and file name for the control.

If you select the Calendar Control, and then click **Create**, MATLAB displays information like:

```
h =  
    COM.mscal.calendar.7  
info =  
    [1x20 char]    'MSCAL.Calendar.7'    [1x41 char]
```

To expand the `info` cell array, type:

```
info{:}
```

MATLAB displays:

```
ans =
```



```
Calendar Control 9.0
ans =
    MSCAL.Calendar.7
ans =
    D:\Applications\MSOffice\Office\MSCAL.OCX
```

## Creating Control Objects from the Command Line

If you already know which control you want and you know its ProgID, use the `actxcontrol` function to create an instance of the control.

The ProgID is the only required input to this function. Additionally, you can select which figure window to put the control in, where to position it in the window, and what size to make it. You can also register events you want the control to respond to, or set the initial state of the control by reading that state from a file. See the `actxcontrol` reference page for a full explanation of its input arguments.

The `actxcontrol` function returns a handle to the primary interface to the object. Use this handle to reference the object in other COM function calls. You can also use the handle to obtain more interfaces to the object. For more information on using interfaces, see “COM Object Interfaces” on page 13-32.

## Repositioning the Control in a Figure Window

After creating a control, you can change its shape and position in the window with the `move` function.

Observe what happens to the object created in the last section when you specify new origin coordinates (70, 120) and new width and height dimensions of 400 and 350:

```
move(h,[70 120 400 350]);
```

## Limitations to ActiveX Support

A MATLAB COM ActiveX control container does not in-place activate controls until they are visible.

## Creating a COM Server

### Instantiating a DLL Component

To create a server for a component implemented as a dynamic link library (DLL), use the `actxserver` function. MATLAB creates an instance of the component in the same process that contains the client application.

The syntax for `actxserver`, when used with a DLL component, is `actxserver(ProgID)`, where `ProgID` is the programmatic identifier for the component.

`actxserver` returns a handle to the primary interface to the object. Use this handle to reference the object in other COM function calls. You can also use the handle to obtain more interfaces to the object. For more information on using interfaces, see “COM Object Interfaces” on page 13-32.

Unlike Microsoft ActiveX controls, any user interface displayed by the server appears in a separate window.

You cannot use a 32-bit in-process DLL COM object in a 64-bit MATLAB application. For information about this restriction, see <http://www.mathworks.com/matlabcentral/answers/95116-why-am-i-not-able-to-use-32-bit-dll-com-objects-in-64-bit-matlab-7-3-r2006b>.

### **Instantiating an EXE Component**

You can use the `actxserver` function to create a server for a component implemented as an executable (EXE). In this case, MATLAB instantiates the component in an out-of-process server.

The syntax for `actxserver` to create an executable is `actxserver(ProgID, sysname)`. `ProgID` is the programmatic identifier for the component, and `sysname` is an optional argument used in configuring a distributed COM (DCOM) system.

`actxserver` returns a handle to the primary interface to the COM object. Use this handle to reference the object in other COM function calls. You can also use the handle to obtain more interfaces to the object. For more information on using interfaces, see “COM Object Interfaces” on page 13-32.

Any user interface displayed by the server appears in a separate window.

This example creates a COM server application running the Microsoft Excel spreadsheet program. The handle is assigned to `h`.

```
h = actxserver('Excel.Application')
```

MATLAB displays:

```
h =  
    COM.excel.application
```

MATLAB can programmatically connect to an instance of a COM Automation server application that is already running on your computer. To get a reference to such an application, use the `actxGetRunningServer` function.

This example gets a reference to the Excel program, which must already be running on your system. The returned handle is assigned to `h`.

```
h = actxGetRunningServer('Excel.Application')
```

MATLAB displays:

```
h =  
    COM.excel.application
```

### **See Also**

`actxcontrol` | `actxGetRunningServer` | `actxserver`

## Handle COM Data in MATLAB

### In this section...

“Passing Data to COM Objects” on page 13-12

“Handling Data from COM Objects” on page 13-14

“Unsupported Types” on page 13-15

“Passing MATLAB Data to ActiveX Objects” on page 13-15

“Passing MATLAB SAFEARRAY to COM Object” on page 13-15

“Reading SAFEARRAY from COM Objects in MATLAB Applications” on page 13-17

“Displaying MATLAB Syntax for COM Objects” on page 13-18

### Passing Data to COM Objects

When you use a COM object in a MATLAB command, the MATLAB types you pass in the call are converted to types native to the COM object. MATLAB performs this conversion on each argument that is passed. This section describes the conversion.

MATLAB converts MATLAB arguments into types that best represent the data to the COM object. The following table shows all the MATLAB base types for passed arguments and the COM types defined for input arguments. Each row shows a MATLAB type followed by the possible COM argument matches. For a description of COM variant types, see the table in “Handling Data from COM Objects” on page 13-14.

MATLAB Argument	Closest COM Type	Allowed Types
handle	VT_DISPATCH VT_UNKNOWN	VT_DISPATCH VT_UNKNOWN
character vector	VT_BSTR	VT_LPWSTR VT_LPSTR VT_BSTR VT_FILETIME VT_ERROR VT_DECIMAL VT_CLSID VT_DATE
int16	VT_I2	VT_I2

MATLAB Argument	Closest COM Type	Allowed Types
uint16	VT_UI2	VT_UI2
int32	VT_I4	VT_I4 VT_INT
uint32	VT_UI4	VT_UI4 VT_UINT
int64	VT_I8	VT_I8
uint64	VT_UI8	VT_UI8
single	VT_R4	VT_R4
double	VT_R8	VT_R8 VT_CY
logical	VT_BOOL	VT_BOOL
char	VT_I1	VT_I1 VT_UI1

### Variant Data

`variant` is any data type except a structure or a sparse array. (For more information, see “Fundamental MATLAB Classes”.)

When used as an input argument, MATLAB treats `variant` and `variant(pointer)` the same way.

If you pass an empty array (`[]`) of type `double`, MATLAB creates a `variant(pointer)` set to `VT_EMPTY`. Passing an empty array of any other numeric type is not supported.

MATLAB Argument	Closest COM Type	Allowed Types
<code>variant</code>	VT_VARIANT	VT_VARIANT VT_USERDEFINED VT_ARRAY
<code>variant(pointer)</code>	VT_VARIANT	VT_VARIANT   VT_BYREF

### SAFEARRAY Data

When a COM method identifies a `SAFEARRAY` or `SAFEARRAY(pointer)`, the MATLAB equivalent is a matrix.

MATLAB Argument	Closest COM Type	Allowed Types
SAFEARRAY	VT_SAFEARRAY	VT_SAFEARRAY
SAFEARRAY(pointer)	VT_SAFEARRAY	VT_SAFEARRAY   VT_BYREF

## Handling Data from COM Objects

Data returned from a COM object is often incompatible with MATLAB types. When this occurs, MATLAB converts the returned value to a data type native to the MATLAB language. This section describes the conversion performed on the various types that can be returned from COM objects.

The following table shows how MATLAB converts data from a COM object into MATLAB variables.

COM Variant Type	Description	MATLAB Representation
VT_DISPATCH VT_UNKNOWN	IDispatch * IUnknown * MATLAB does not support the IUnknown and IDispatch interfaces with 64-bit MATLAB.	handle
VT_LPWSTR VT_LPSTR VT_BSTR VT_FILETIME VT_ERROR VT_DECIMAL VT_CLSID VT_DATE	wide null terminated string null terminated string OLE Automation string FILETIME SCODE 16-byte fixed point Class ID date	character vector
VT_INT VT_UINT VT_I2 VT_UI2 VT_I4 VT_UI4 VT_R4 VT_R8	signed machine int unsigned machine int 2-byte signed int unsigned short 4-byte signed int unsigned long 4-byte real 8-byte real	double

COM Variant Type	Description	MATLAB Representation
VT_CY	currency	
VT_I8	signed int64	int64
VT_UI8	unsigned int64	uint64
VT_BOOL		logical
VT_I1 VT_UI1	signed char unsigned char	char
VT_VARIANT VT_USERDEFINED VT_ARRAY	VARIANT * user-defined type SAFEARRAY*	variant
VT_VARIANT   VT_BYREF	VARIANT * void* for local use	variant(pointer)
VT_SAFEARRAY	use VT_ARRAY in VARIANT	SAFEARRAY
VT_SAFEARRAY   VT_BYREF		SAFEARRAY(pointer)

## Unsupported Types

MATLAB does not support the following COM interface types and displays the warning `ActiveX - unsupported VARIANT type encountered`.

- Structure
- Sparse array
- Multidimensional SAFEARRAYs (greater than two dimensions)
- Write-only properties

## Passing MATLAB Data to ActiveX Objects

The tables also show the mapping of MATLAB types to COM types that you must use to pass data from MATLAB to an Microsoft ActiveX object. For all other types, MATLAB displays the warning `ActiveX - invalid argument type or value`.

## Passing MATLAB SAFEARRAY to COM Object

The `SAFEARRAY` data type is a standard way to pass arrays between COM objects. This section explains how MATLAB passes `SAFEARRAY` data to a COM object.

- “Default Behavior in MATLAB Software” on page 13-16
- “Examples” on page 13-16
- “How to Pass a Single-Dimension SAFEARRAY” on page 13-17
- “Passing SAFEARRAY by Reference” on page 13-17

### **Default Behavior in MATLAB Software**

MATLAB represents an  $m$ -by- $n$  matrix as a two-dimensional SAFEARRAY, where the first dimension has  $m$  elements and the second dimension has  $n$  elements. MATLAB passes the SAFEARRAY by value.

### **Examples**

The following examples use a COM object that expects a SAFEARRAY input parameter.

When MATLAB passes a 1-by-3 array:

```
B = [2 3 4]
B =
     2     3     4
```

the object reads:

```
No. of dimensions: 2
Dim: 1,   No. of elements: 1
Dim: 2,   No. of elements: 3
Elements:
  2.0
  3.0
  4.0
```

When MATLAB passes a 3-by-1 array:

```
C = [1;2;3]
C =
     1
     2
     3
```

the object reads:

```
No. of dimensions: 2
Dim: 1,   No. of elements: 3
Dim: 2,   No. of elements: 1
```



Elements:

```
1.0
2.0
3.0
```

When MATLAB passes a 2-by-4 array:

```
D = [2 3 4 5;5 6 7 8]
```

D =

```
2     3     4     5
5     6     7     8
```

the object reads:

No. of dimensions: 2

Dim: 1, No. of elements: 2

Dim: 2, No. of elements: 4

Elements:

```
2.0
3.0
4.0
5.0
5.0
6.0
7.0
8.0
```

### How to Pass a Single-Dimension SAFEARRAY

For information about passing arguments as one-dimensional arrays to a COM object, see <http://www.mathworks.com/matlabcentral/answers/92424-how-can-i-pass-arguments-to-an-activex-server-from-matlab-7-0-r14-as-one-dimensional-arrays>.

### Passing SAFEARRAY by Reference

For information about passing arguments by reference to a COM object, see <http://www.mathworks.com/matlabcentral/answers/94888-how-can-i-pass-arguments-by-reference-to-an-activex-server-from-matlab-7-0-r14>.

## Reading SAFEARRAY from COM Objects in MATLAB Applications

This section explains how MATLAB reads SAFEARRAY data from a COM object.

MATLAB reads a one-dimensional SAFEARRAY with  $n$  elements from a COM object as a 1-by- $n$  matrix. For example, using methods from the MATLAB sample control `mwsamp`, type:

```
h=actxcontrol('mwsamp.mwsampctrl.1')
a = GetI4Vector(h)
```

MATLAB displays:

```
a =
      1      2      3
```

MATLAB reads a two-dimensional SAFEARRAY with  $n$  elements as a 2-by- $n$  matrix. For example:

```
a = GetR8Array(h)
```

MATLAB displays:

```
a =
      1      2      3
      4      5      6
```

MATLAB reads a three-dimensional SAFEARRAY with two elements as a 2-by-2-by-2 cell array. For example:

```
a = GetBSTRArray(h)
```

MATLAB displays:

```
a(:,:,1) =
      '1 1 1'      '1 2 1'
      '2 1 1'      '2 2 1'

a(:,:,2) =
      '1 1 2'      '1 2 2'
      '2 1 2'      '2 2 2'
```

## Displaying MATLAB Syntax for COM Objects

To determine which MATLAB types to use when passing arguments to COM objects, use the `invoke` or `methodsvi` functions. These functions list all the methods found in an object, along with a specification of the types required for each argument.

Consider a server called `MyApp`, which has a single method `TestMeth1` with the following syntax:

```
HRESULT TestMeth1 ([out, retval] double* dret);
```

This method has no input argument, and it returns a variable of type `double`. The following **pseudo-code** displays the MATLAB syntax for calling the method.

```
h = actxserver('MyApp');
invoke(h)
```

MATLAB displays:

```
ans =
    TestMeth1 = double TestMeth1 (handle)
```

The signature of `TestMeth1` is:

```
double TestMeth1(handle)
```

MATLAB requires you to use an object handle as an input argument for every method, in addition to any input arguments required by the method itself.

Use one of the following **pseudo-code** commands to create the variable `var`, which is of type `double`.

```
var = h.TestMeth1;
```

or:

```
var = TestMeth1(h);
```

Although the following syntax is correct, its use is discouraged:

```
var = invoke(h, 'TestMeth1');
```

Now consider the server called `MyApp1` with the following methods:

```
HRESULT TestMeth1 ([out, retval] double* dret);
HRESULT TestMeth2 ([in] double* d, [out, retval] double* dret);
HRESULT TestMeth3 ([out] BSTR* sout,
                  [in, out] double* dinout,
                  [in, out] BSTR* sinout,
                  [in] short sh,
                  [out] long* ln,
```

```
[in, out] float* b1,  
[out, retval] double* dret);
```

Using the `invoke` function, MATLAB displays the list of methods:

```
ans =  
TestMeth1 = double TestMeth1 (handle)  
TestMeth2 = double TestMeth2 (handle, double)  
TestMeth3 = [double, string, double, string, int32, single] ...  
            TestMeth3(handle, double, string, int16, single)
```

`TestMeth2` requires an input argument `d` of type `double`, and returns a variable `dret` of type `double`. Some **pseudo-code** examples of calling `TestMeth2` are:

```
var = h.TestMeth2(5);
```

or:

```
var = TestMeth2(h, 5);
```

`TestMeth3` requires multiple input arguments, as indicated within the parentheses on the right side of the equal sign, and returns multiple output arguments, as indicated within the brackets on the left side of the equal sign.

```
[double, string, double, string, int32, single] %output arguments  
TestMeth3(handle, double, string, int16, single) %input arguments
```

The first input argument is the required `handle`, followed by four input arguments.

```
TestMeth3(handle, in1, in2, in3, in4)
```

The first output argument is the return value `retval`, followed by five output arguments.

```
[retval, out1, out2, out3, out4, out5]
```

This is how the arguments map into a MATLAB command:

```
[dret, sout, dinout, sinout, ln, b1] = TestMeth3(handle, ...  
                                                dinout, sinout, sh, b1)
```

where `dret` is `double`, `sout` is `string`, `dinout` is `double` and is both an input and an output argument, `sinout` is `string` (input and output argument), `ln` is `int32`, `b1` is `single` (input and output argument), `handle` is the handle to the object, and `sh` is `int16`.

## COM Object Properties

In this section...
“MATLAB Functions for Object Properties” on page 13-21
“Work with Multiple Objects” on page 13-21
“Enumerated Values for Properties” on page 13-22
“Property Inspector” on page 13-22
“Custom Properties” on page 13-23
“Properties That Take Arguments” on page 13-23

### MATLAB Functions for Object Properties

You can get the value of a property and, sometimes, change the value. You also can add custom properties.

Property names are not case-sensitive. You can abbreviate them as long as the name is unambiguous.

Function	Description
<code>get</code>	List one or more properties and their values.
<code>set</code>	Set the value of one or more properties.
<code>isprop</code>	Determine if an item is a property of a COM object.
<code>addproperty</code>	Add a custom property to a COM object.
<code>deleteproperty</code>	Remove a custom property from a COM object.
<code>inspect</code>	Open the Property Inspector to display and modify property values.
<code>propedit</code>	Display the built-in property page of the control, if any.

### Work with Multiple Objects

You can use the `get` and `set` functions on more than one object at a time by creating a vector of object handles and using these commands on the vector. To get or set values for multiple objects, use the functional form of the `get` and `set` functions. Use dot notation, for example `h.propname`, on scalar objects only.

## Enumerated Values for Properties

Enumeration makes examining and changing properties easier because each possible value for the property is assigned text to represent it. For example, one of the values for the `DefaultSaveFormat` property in a Microsoft Excel spreadsheet is `xlUnicodeText`. This text is easier to remember than a numeric value like 57.

## Property Inspector

The Property Inspector enables you to access the properties of COM objects. To open the Property Inspector, use the `inspect` function from the MATLAB command line or double-click the object in the MATLAB Workspace browser.

For example, create an Excel object. Then set the `DefaultFilePath` property to an existing folder, `C:\ExcelWork`.

```
h = actxserver('Excel.Application');  
h.DefaultFilePath = 'C:\ExcelWork';
```

Display the properties of the object.

```
inspect(h)
```

Scroll down until you see the `DefaultFilePath` property that you just changed, `C:\ExcelWork`.

Using the Property Inspector, change `DefaultFilePath` once more, this time to another existing folder, `MyWorkDirectory`. To do this, select the value at the right and type the new value.

Now go back to the MATLAB Command Window and confirm that the `DefaultFilePath` property has changed as expected.

```
h.DefaultFilePath  
ans =  
C:\MyWorkDirectory
```

---

**Note:** If you modify properties at the MATLAB command line, refresh the Property Inspector window to see the change reflected there. Refresh the Property Inspector window by reinvoking the `inspect` function on the object.

---

## Using the Property Inspector on Enumerated Values

A list button next to a property value indicates that the property accepts enumerated values. To see the values, click anywhere in the field on the right. For example, the `Cursor` property has four enumerated values. The current value `xIDefault` is displayed in the field next to the property name.

To change the value, use the list button to display the options for that property, and then click the desired value.

## Custom Properties

You can add your own properties to an instance of a control using the `addproperty` function.

To remove custom properties from a control, use the `deleteproperty` function.

## Properties That Take Arguments

Some COM objects have properties that accept input arguments. Internally, MATLAB handles these properties as methods, which means you use the `methods` or `invoke` functions (not the `get` function) to view the property.

## Related Examples

- “Change Cursor in Spreadsheet” on page 13-46
- “Add Position Property to `mwsamp` Control” on page 13-57
- “Change Row Height in Range of Spreadsheet Cells” on page 13-42

## More About

- “Exploring Properties” on page 13-38

## COM Methods

### In this section...

“Getting Method Information” on page 13-24

“Calling Object Methods” on page 13-24

“Specifying Enumerated Parameters” on page 13-25

“Skipping Optional Input Arguments” on page 13-25

“Returning Multiple Output Arguments” on page 13-26

### Getting Method Information

You execute, or *invoke*, COM functions or methods belonging to COM objects. Method names are case-sensitive. You cannot abbreviate them.

To see what methods a COM object supports, use one of the following functions. Each function presents specific information, as described in the table. For information about using a method, refer to your vendor documentation.

Function	Output
<code>methodsview</code>	Graphical display of function names and signatures
<code>methods</code> with <code>-full</code> qualifier	Cell array of function names and signatures, sorted alphabetically
<code>methods</code>	Cell array of function names only, sorted alphabetically, with uppercase names listed first
<code>invoke</code>	Cell array of function names and signatures

### Calling Object Methods

MATLAB supports the following syntaxes to call methods on an object.

- By method name:

```
outputvalue = methodname(object, 'arg1', 'arg2', ...);
```



- By *dot notation*:

```
outputvalue = object.methodname('arg1', 'arg2', ...);
```

- Using explicit syntax:

```
outputvalue = invoke(object, 'methodname', 'arg1', 'arg2', ...);
```

The `methodsview` and `methods -full` commands show what data types to use for input and output arguments.

You cannot use dot syntax and must explicitly call the `get`, `set`, and `invoke` functions under the following conditions:

- To access a property or method that is not a public member of the object class.
- To access a property or method that is not in the type library for the control or server.
- To access properties that take arguments. MATLAB treats these properties like methods.
- To access properties on a vector of objects, use the `get` and `set` functions.

You cannot invoke a method on multiple COM objects, even if you call the `invoke` function explicitly.

## Specifying Enumerated Parameters

Enumeration is a way of assigning a descriptive name to a symbolic value. MATLAB supports enumeration for parameters passed to methods under the condition that the type library in use reports the parameter as `ENUM`, and only as `ENUM`.

---

**Note:** MATLAB does not support enumeration for any parameter that the type library reports as both `ENUM` and `Optional`.

---

## Skipping Optional Input Arguments

When calling a method that takes optional input arguments, you can skip an optional argument by specifying an empty array (`[]`) in its place. For example, the syntax for calling a method with second argument `arg2` not specified is:

```
methodname(handle, arg1, [], arg3);
```

## Returning Multiple Output Arguments

If a server function supports multiple outputs, you can return any or all those outputs to a MATLAB client.

The following syntax shows a server function `functionname` called by the MATLAB client. `retval` is the first output argument, or return value. The other output arguments are `out1`, `out2`, ....

```
[retval out1 out2 ...] = functionname(handle,in1,in2,...);
```

MATLAB uses the pass-by-reference capabilities in COM to implement this feature. Pass-by-reference is a COM feature; MATLAB does not support pass-by-reference.

## Related Examples

- “Change Row Height in Range of Spreadsheet Cells” on page 13-42
- “Redraw Circle in `mwsamp` Control” on page 13-48
- “Insert Spreadsheet After First Sheet” on page 13-47

## More About

- “Handle COM Data in MATLAB” on page 13-12

## COM Events

An *event* is typically a user-initiated action that takes place in a server application, which often requires a reaction from the client. For example, if you click the mouse at a particular location in a server interface window, the client application can respond. When an event is *fired*, the server communicates this occurrence to the client. If the client is *listening* for this particular type of event, it responds by executing a routine called an *event handler*.

The MATLAB COM client can subscribe to and handle the events fired by a Microsoft ActiveX control or a COM server. Select the events you want the client to listen to. Register each event with an event handler to be used in responding to the event. When a registered event takes place, the control or server notifies the client, which responds by executing the appropriate event handler routine. You can write event handlers as MATLAB functions.

To identify events the control or server can respond to, use the `events` function.

To register events you want to respond to, use the `registerevent` function. The MATLAB client responds only to events you have registered. If you register the same event name to the same callback handler multiple times, MATLAB executes the event only once.

For ActiveX controls, you can register events at the time you create an instance of the control using the `actxcontrol` function.

To identify registered events, use the `eventlisteners` function.

To respond to events as they occur, create event handlers that have been registered for that event. You can implement these routines as MATLAB functions.

To unregister events you no longer want to listen to, use the `unregisterevent` or `unregisterallevents` function.

---

**Note:** MATLAB does not support asynchronous events.

---

---

**Note:** MATLAB does not support interface events from a Custom server.

---

### **See Also**

actxcontrol | eventlisteners | events | registerevent |  
unregisterallevents | unregisterevent

### **Related Examples**

- “Read Spreadsheet Data Using Excel as Automation Server” on page 12-15
- “Combine Event Handlers as MATLAB Local Functions” on page 13-52

### **More About**

- “COM Event Handlers” on page 13-29

## COM Event Handlers

### In this section...

“Overview of Event Handling” on page 13-29

“Arguments Passed to Event Handlers” on page 13-29

“Event Structure” on page 13-30

### Overview of Event Handling

For controls, register handler functions either at the time you create an instance of the control (using `actxcontrol`), or any time afterward (using `registerevent`).

For servers, use `registerevent` to register events.

Use `events` to list all the events a COM object recognizes.

### Arguments Passed to Event Handlers

When a registered event is triggered, MATLAB passes information from the event to its handler function, as shown in the following table.

#### Arguments Passed by MATLAB Functions

Arg. No.	Contents	Format
1	Object name	MATLAB COM class
2	Event ID	double
3	Start of Event Argument List	As passed by the control
end - 2	End of Event Argument List (Argument N)	As passed by the control
end - 1	Event Structure	structure
end	Event Name	char array

When writing an event handler function, use the Event Name argument to identify the source of the event. Get the arguments passed by the control from the Event Argument List (arguments 3 through `end - 2`). All event handlers must accept a variable number of arguments:

```
function event (varargin)
if (strcmp(varargin{end}, 'MouseDown')) % Check the event name
    x_pos = varargin{5}; % Read 5th Event Argument
    y_pos = varargin{6}; % Read 6th Event Argument
end
```

---

**Note:** The values passed vary with the particular event and control being used.

---

## Event Structure

The Event Structure argument passed by MATLAB contains the fields shown in the following table.

### Fields of the Event Structure

Field Name	Description	Format
Type	Event Name	char array
Source	Control Name	MATLAB COM class
EventID	Event Identifier	double
Event Arg Name 1	Event Arg Value 1	As passed by the control
Event Arg Name 2	Event Arg Value 2	As passed by the control
etc.	Event Arg N	As passed by the control

For example, when the `MouseDown` event of the `mwsamp2` control is triggered, MATLAB passes this Event Structure to the registered event handler:

```
Type: 'MouseDown'
Source: [1x1 COM.mwsamp.mwsampctr1.2]
EventID: -605
Button: 1
Shift: 0
    x: 27
    y: 24
```

## See Also

`actxcontrol` | `events` | `registerevent`

## Related Examples

- “Display Event Messages from `mwsamp` Control” on page 13-54
- “Combine Event Handlers as MATLAB Local Functions” on page 13-52

## More About

- “COM Events” on page 13-27

## COM Object Interfaces

### In this section...

“IUnknown and IDispatch Interfaces” on page 13-32

“Custom Interfaces” on page 13-33

### IUnknown and IDispatch Interfaces

When you invoke the `actxserver` or `actxcontrol` functions, the MATLAB software creates the server and returns a handle to the server interface as a means of accessing its properties and methods. The software uses the following process to determine which handle to return:

- 1 First get a handle to the IUnknown interface from the component. All COM components are required to implement this interface.
- 2 Attempt to get the IDispatch interface. If IDispatch is implemented, return a handle to this interface. If IDispatch is not implemented, return the handle to IUnknown.

### Additional Interfaces

Components often provide additional interfaces, based on IDispatch, that are implemented as properties. Like any other property, you obtain these interfaces using the MATLAB `get` function.

For example, a Microsoft Excel component contains numerous interfaces. To list these interfaces, along with Excel properties, type:

```
h = actxserver('Excel.Application');  
get(h)
```

MATLAB displays information like:

```
Application: [1x1 Interface.Microsoft_Excel_9.0_
Object_Library._Application]
  Creator: 'xlCreatorCode'
  Parent: [1x1 Interface.Microsoft_Excel_9.0_
Object_Library._Application]
  ActiveCell: []
  ActiveChart: [1x50 char]
```



To see if `Workbooks` is an interface, type:

```
w = h.Workbooks
```

MATLAB displays:

```
w =
    Interface.Microsoft_Excel_9.0_Object_Library.Workbooks
```

The information displayed depends on the version of the Excel software you have on your system.

For examples using Excel in MATLAB, see:

- “Write Data to Excel Spreadsheet Using ActiveX” on page 13-44
- “Read Spreadsheet Data Using Excel as Automation Server” on page 12-15
- `actxserver`

## Custom Interfaces

The MATLAB COM Interface supports custom interfaces for the following client/server configurations:

- “MATLAB Client and In-Process Server” on page 12-22
- “MATLAB Client and Out-of-Process Server” on page 12-23

Limitations to custom interface support are:

- Custom interfaces are not supported on a 64-bit version of MATLAB.
- You cannot invoke functions with optional parameters.

Once you have created a server, you can query the server component to see if any custom interfaces are implemented using the `interfaces` function.

For example, if you have a component with the ProgID `mytestenv.calculator`, you can see its custom interfaces using the commands:

```
h = actxserver('mytestenv.calculator');
customlist = h.interfaces
```

MATLAB displays the interfaces, which might be:

```
customlist =  
    ICalc1  
    ICalc2  
    ICalc3
```

To get the handle to a particular interface, use the `invoke` function:

```
c1 = invoke(h, 'ICalc1')  
c1 =  
    Interface.Calc_1.0_Type_Library.ICalc_Interface
```

Use this handle `c1` to access the properties and methods of the object through this custom interface `ICalc1`.

For example, to list the properties, use:

```
get(c1)  
    background: 'Blue'  
    height: 10  
    width: 0
```

To list the methods, use:

```
invoke(c1)  
    Add = double Add(handle, double, double)  
    Divide = double Divide(handle, double, double)  
    Multiply = double Multiply(handle, double, double)  
    Subtract = double Subtract(handle, double, double)
```

To add and multiply numbers using the `Add` and `Multiply` methods of the object, use:

```
sum = Add(c1,4,7)  
sum =  
    11  
  
prod = c1.Multiply(4, 7)  
prod =  
    28
```

## More About

- “Supported Client/Server Configurations” on page 12-22

## Save and Delete COM Objects

### In this section...

“Functions for Saving and Restoring COM Objects” on page 13-35

“Releasing COM Interfaces and Objects” on page 13-35

### Functions for Saving and Restoring COM Objects

Use these MATLAB functions to save and restore the state of a COM control object.

Function	Description
load	Load and initialize a COM control object from a file
save	Write and serialize a COM control object to a file

Save, or *serialize*, the current state of a COM control to a file using the **save** function. *Serialization* is the process of saving an object onto a storage medium (such as a file or a memory buffer) or transmitting it across a network connection link in binary form.

---

**Note:** MATLAB supports the COM save and load functions for controls only.

---

### Releasing COM Interfaces and Objects

Use these MATLAB functions to release or delete a COM object or interface.

Function	Description
delete	Delete a COM object or interface
release	Release a COM interface

When you no longer need an interface, use the **release** function to release the interface and reclaim the memory used by it. When you no longer need a control or server, use the **delete** function to delete it. Alternatively, you can use the **delete** function to both release all interfaces for the object and delete the server or control.

---

**Note:** In versions of MATLAB earlier than 6.5, failure to explicitly release interface handles or delete the control or server often results in a memory leak. This is true even if

the variable representing the interface or COM object has been reassigned. In MATLAB version 6.5 and later, the control or server, along with all interfaces to it, is destroyed on reassignment of the variable or when the variable representing a COM object or interface goes out of scope.

---

When you delete or close a figure window containing a control, MATLAB automatically releases all interfaces for the control. MATLAB also automatically releases all handles for an Automation server when you exit the program.

### **Related Examples**

- “Save `mwsamp2` COM Control” on page 13-58

## MATLAB Application as DCOM Client

Distributed Component Object Model (DCOM) is a protocol that allows clients to use remote COM objects over a network. Also, MATLAB can be used as a DCOM client with remote Automation servers if the operating system on which MATLAB is running is DCOM enabled.

---

**Note:** If you use MATLAB as a remote DCOM server, all MATLAB windows appears on the remote machine.

---

## Explore COM Objects

A COM object has properties, methods, events, and interfaces. Your vendor documentation describes these features, but you can also learn about your object using MATLAB commands.

### In this section...

“Exploring Properties” on page 13-38

“Exploring Methods” on page 13-39

“Exploring Events” on page 13-39

“Exploring Interfaces” on page 13-40

“Identifying Objects and Interfaces” on page 13-40

## Exploring Properties

A *property* is information that is associated with a COM object. To see a list of properties of an object, use the COM `get` function. Alternatively, use the MATLAB Property Inspector, a user interface to display and modify properties. For example, to list all properties of a Microsoft Excel object type:

```
myApp = actxserver('Excel.Application');  
get(myApp)
```

MATLAB displays the properties for your Excel version. To display a single property, type:

```
myApp.OrganizationName
```

```
ans =
```

```
MathWorks, Inc.
```

MATLAB displays the value for your application.

To open the Property Inspector, choose one of the following.

- Call the `inspect` function from the MATLAB command line:

```
inspect(myApp)
```

- Double-click the `myApp` object in the MATLAB Workspace browser.

MATLAB opens the Inspector window. Scroll down until you see the `OrganizationName` property, the same value returned by the `get` function.

## Exploring Methods

A *method* is a procedure you call to perform a specific action on the COM object. For example, to list all methods supported by the Excel object, type:

```
myApp = actxserver('Excel.Application');  
methodsviw(myApp)
```

MATLAB opens a window showing the method signatures for `COM.Excel_Application` objects.

## Exploring Events

An *event* is typically a user-initiated action that takes place in a server application, which often requires a reaction from the client. For example, clicking the mouse at a particular location in a server interface window might require the client to respond. When an event is *fired*, the server communicates this occurrence to the client. If the client is *listening* for this particular type of event, it responds by executing a routine called an *event handler*.

Use the `events` function to list all events known to the control or server and use the `eventlisteners` function to list registered events.

For example, to list the events for the Microsoft Internet Explorer web browser, type:

```
myNet = actxserver('internetexplorer.application');  
events(myNet)
```

MATLAB displays the events for your Internet Explorer version. To see which events have event handlers, type:

```
eventlisteners(myNet)
```

```
ans =  
    {}
```

An empty result means that no events are registered.

## Exploring Interfaces

An *interface* is a set of related functions used to access the data of a COM object. When you create a COM object using the `actxserver` or `actxcontrol` function, MATLAB returns a handle to an interface. Use the `get` and `interfaces` functions to see other interfaces implemented by your object.

For example, to see interfaces of an Excel object, type:

```
e = actxserver('Excel.Application');
get(e)
```

MATLAB displays the properties, including interfaces, for your Excel version. For example, `Workbooks` is an interface.

```
e.Workbooks
```

```
ans =
```

```
Interface.000208DB_0000_0000_C000_000000000046
```

To explore the `Workbooks` interface, create a `workbooks` object and use the relevant MATLAB commands.

```
w = e.Workbooks;
```

## Identifying Objects and Interfaces

Function	Description
<code>class</code>	Return the class of an object.
<code>isa</code>	Determine if an object is of a given MATLAB class.
<code>iscom</code>	Determine if the input is a COM or ActiveX object.
<code>isevent</code>	Determine if an item is an event of a COM object.
<code>ismethod</code>	Determine if an item is a method of a COM object.
<code>isprop</code>	Determine if an item is a property of a COM object.
<code>isinterface</code>	Determine if the input is a COM interface.

### See Also

[eventlisteners](#) | [events](#) | [get](#) | [inspect](#) | [interfaces](#) | [methodsview](#)



## **More About**

- “COM Object Properties” on page 13-21
- “Property Inspector” on page 13-22
- “COM Methods” on page 13-24
- “COM Events” on page 13-27
- “COM Event Handlers” on page 13-29

## **External Websites**

- Microsoft Excel 2013 developer reference

## Change Row Height in Range of Spreadsheet Cells

This example shows how to change the height of a row, defined by a Range object, in a spreadsheet.

The Excel Range object is a property that takes input arguments. MATLAB treats such a property as a method. Use the `methods` function to get information about creating a Range object.

Create a Worksheet object `ws`.

```
e = actxserver('Excel.Application');  
wb = Add(e.Workbooks);  
e.Visible = 1;  
ws = e.ActiveSheet;
```

Display the default height of all the rows in the worksheet.

```
ws.StandardHeight
```

```
ans =
```

```
14.4000
```

Display the function syntax for creating a Range object.

```
methods(ws, '-full')
```

Search the displayed list for the Range entry: `handle Range(handle, Variant, Variant(Optional))`

Create a Range object consisting of the first row.

```
wsRange = ws.Range('A1');
```

Increase the row height.

```
wsRange.RowHeight = 25;
```

Open the worksheet, click in row 1, and notice the height.

Close the workbook without saving.

```
wb.Saved = 1;
```

`Close(e.Workbook)`

Close the application.

`Quit(e)`  
`delete(e)`

## **See Also**

methods

## **More About**

- “Properties That Take Arguments” on page 13-23

## **External Websites**

- [Worksheet.Range Property \(Excel\) Office 2013](#)

## Write Data to Excel Spreadsheet Using ActiveX

This example shows how to write a MATLAB matrix to an Excel spreadsheet. For alternatives to exporting MATLAB data to a Microsoft Excel spreadsheet, see the functions and examples in “Spreadsheets”.

Create an Excel object.

```
e = actxserver('Excel.Application');
```

Add a workbook.

```
eWorkbook = e.Workbooks.Add;  
e.Visible = 1;
```

Make the first sheet active.

```
eSheets = e.ActiveWorkbook.Sheets;  
eSheet1 = eSheets.get('Item',1);  
eSheet1.Activate
```

Put MATLAB data into the worksheet.

```
A = [1 2; 3 4];  
eActivesheetRange = get(e.Activesheet, 'Range', 'A1:B2');  
eActivesheetRange.Value = A;
```

Read the data back into MATLAB, where array B is a cell array.

```
eRange = get(e.Activesheet, 'Range', 'A1:B2');  
B = eRange.Value;
```

Convert the data to a double matrix. Use the following command if the cell array contains only scalar values.

```
B = reshape([B{:}], size(B));
```

Save the workbook in a file.

```
SaveAs(eWorkbook, 'myfile.xls')
```

If the Excel program displays a dialog box about saving the file, select the appropriate response to continue.

If you saved the file, then close the workbook.

```
eWorkbook.Saved = 1;  
Close(eWorkbook)
```

Quit the Excel program and delete the server object.

```
Quit(e)  
delete(e)
```

---

**Note:** Make sure that you close workbook objects you create to prevent potential memory leaks.

---

## See Also

[xlswrite](#)

## More About

- [“Import and Export Dates to Excel Files”](#)

## External Websites

- [Microsoft Excel 2013 developer reference](#)

## Change Cursor in Spreadsheet

This example shows how to change the cursor icon in an Excel spreadsheet.

Create a COM server running a Microsoft Excel application.

```
h = actxserver('Excel.Application');  
h.Visible = 1;
```

Open the Excel program and notice the cursor.

View the options for the `Cursor` property.

```
set(h, 'Cursor')
```

```
ans =
```

```
    'xlIBeam'  
    'xlDefault'  
    'xlNorthwestArrow'  
    'xlWait'
```

These values are enumerated values, which means they are the only values allowed for the `Cursor` property.

Change the cursor to `'xlIBeam'`

```
h.Cursor = 'xlIBeam';
```

Notice the cursor in the program.

Reset the cursor.

```
h.Cursor = 'xlDefault';
```

```
Quit(h)  
delete(h)
```

Make sure that you close workbook objects you create to prevent potential memory leaks.

### More About

- “Enumerated Values for Properties” on page 13-22

## Insert Spreadsheet After First Sheet

This example shows how to skip an optional input argument in the Excel Add method, used to insert a sheet into a workbook.

The Add method has the following optional input arguments:

- **Before** — The sheet before which to add the new sheet
- **After** — The sheet after which to add the new sheet
- **Count** — The total number of sheets to add
- **Type** — The type of sheet to add

```
e = actxserver('Excel.Application');  
Add(e.Workbooks);  
e.Visible = 1;
```

Create a collection of the three default sheets in the workbook.

```
eSheets = e.ActiveWorkbook.Sheets;
```

Insert a sheet after the first item in the collection, eSheet1.

```
eSheet1 = Item(eSheets,1);  
eNewSheet = Add(eSheets,[],eSheet1);
```

To call Add with the After argument, omit the first argument, Before, by using an empty array [ ] in its place.

Open the workbook and notice Sheet4.

Close the spreadsheet.

Close the application.

```
Quit(e)  
delete(e)
```

### More About

- “Skipping Optional Input Arguments” on page 13-25

### External Websites

- Office 2013 Sheets.Add Method (Excel)

## Redraw Circle in mwsamp Control

This example shows how to call a method of the `mwsamp` control to redraw a circle.

Create the control.

```
myfigure = actxcontrol('mwsamp.mwsampctrl1.2', [0 0 200 200]);
```

MATLAB opens a figure window and displays a circle and text label.

Display the properties of the control.

```
get(myfigure)

    Label: 'Label'
    Radius: 20
    Ret_IDispatch: [1x1 Interface.mwsamp2_ActiveX_Control_module._DMwsamp2]
```

You can change the text displayed in the `Label` property and the radius of the circle.

Display the methods for the `mwsamp` control.

```
methods(myfigure)
```

```
Methods for class COM.mwsamp_mwsampctrl_1:
```

AboutBox	GetR8Array	SetR8	invoke
Beep	GetR8Vector	SetR8Array	load
FireClickEvent	GetVariantArray	SetR8Vector	move
GetBSTR	GetVariantVector	addproperty	propedit
GetBSTRArray	Redraw	constructorargs	release
GetI4	SetBSTR	delete	save
GetI4Array	SetBSTRArray	deleteproperty	send
GetI4Vector	SetI4	events	set
GetIDispatch	SetI4Array	get	
GetR8	SetI4Vector	interfaces	

MATLAB displays the list alphabetically; method names with initial caps are listed before methods with lowercase names.

To use the `Redraw` method, display the method signatures which specify the input and output arguments.

```
methodsviw(myfigure)
```



MATLAB opens a window displaying method signatures for all methods supported by the object. The input argument for the `Redraw` method is the object handle.

Change the radius of circle `myfigure` to 100.

```
myfigure.Radius = 100;  
Redraw(myfigure)
```

Close the figure window and the `methodsvew` window.

## **More About**

- “COM Methods” on page 13-24

## Connect to Existing Excel Application

This example shows how to read data from an open file, `weekly_log.xlsx`, in MATLAB.

MATLAB can access a file that is open by another application by creating a COM server from the MATLAB client, and then opening the file through this server.

Navigate to a folder containing an Excel file, for example, `weekly_log.xlsx`. Open the file in the Excel program.

Open the same file in MATLAB.

```
excelapp = actxserver('Excel.Application');  
wkbk = excelapp.Workbooks;  
wdata = Open(wkbk, 'c:\work\weekly_log.xlsx');
```

Read data in the range D1 and F6 from sheet 2.

```
sheets = wdata.Sheets;  
sheet12 = Item(sheets,2);  
range = get(sheet12, 'Range', 'D1', 'F6');  
range.value
```

```
ans =
```

'Temp.'	'Heat Index'	'Wind Chill'
[78.4200]	[ 32]	[ 37]
[69.7300]	[ 27]	[ 30]
[77.6500]	[ 17]	[ 16]
[74.2500]	[ -5]	[ 0]
[68.1900]	[ 22]	[ 35]

```
Close(wkbk)  
Quit(excelapp)
```

### See Also

`actxserver`

## Display Message for Workbook OnClose Event

This example shows how to handle a COM interface event, how to set up an event in a Microsoft Excel workbook object, and how to handle its `BeforeClose` event.

Create the following event handler file, `OnBeforeCloseWorkbook.m`, in your current folder.

```
function OnBeforeCloseWorkbook(varargin)
disp('BeforeClose event occurred')
```

Create the Excel object and make it visible.

```
x1 = actxserver('Excel.Application');
x1.Visible = 1;
```

Add a workbook.

```
hWbks = x1.Workbooks;
hWorkbook = hWbks.Add;
```

Register the `OnBeforeCloseWorkbook` function for the `OnClose` event.

```
registerevent(hWorkbook, {'BeforeClose' @OnBeforeCloseWorkbook})
```

Close the workbook, which triggers the `Close` event and calls the `OnClose` handler.

```
Close(hWorkbook)
BeforeClose event occurred
Quit(x1)
```

### See Also

`registerevent`

### More About

- “COM Events” on page 13-27

## Combine Event Handlers as MATLAB Local Functions

This example shows how to consolidate event handlers into a single file using local functions.

Create the `mycallbacks.m` file containing three event handler routines, `myclick`, `my2click`, and `mymoused`, implemented as local functions.

```
function a = mycallbacks(str)
a = str2func(str);

function myclick(varargin)
disp('Single click function')

function my2click(varargin)
disp('Double click function')

function mymoused(varargin)
disp('You have reached the mouse down function')
disp('The X position is: ')
double(varargin{5})
disp('The Y position is: ')
double(varargin{6})
```

The call to `str2func` converts the input character vector to a function handle.

Create the control.

```
h = actxcontrol('mwsamp.mwsampctr1.2',[0 0 200 200],gcf,'sampev')
```

Register Click event.

```
registerevent(h,{'Click',mycallbacks('myclick')})
```

### Related Examples

- “Display Event Messages from `mwsamp` Control” on page 13-54

## MATLAB Sample ActiveX Control mwsamp

MATLAB includes an example COM control that draws a circle on the screen, displays some text, and fires events when the user single- or double-clicks the control.

Create the control by running the `mwsamp` function in the `matlabroot\toolbox\matlab\winfun` folder, or type:

```
h = actxcontrol('mwsamp.mwsampctrl1.2',[0 0 300 300]);
```

This control is in the folder with its *type library*. The type library is a binary file used by COM tools to decipher the capabilities of the control.

Display the events for this control.

```
allEvents = events(h)
```

```
allEvents =
```

```
    Click: 'void Click()'
   Db1Click: 'void Db1Click()'
  MouseDown: 'void MouseDown(int16 Button, int16 Shift, Variant x, Vari...'
  Event_Args: 'void Event_Args(int16 typeshort, int32 typelong, double t...'
```

`allEvents` is a structure array. Each field of the structure is the name of an event handler and the value of that field contains the signature for the handler routine. For example:

```
allEvents.MouseDown
```

```
ans =
```

```
void MouseDown(int16 Button, int16 Shift, Variant x, Variant y)
```

### See Also

`actxcontrol`

### Related Examples

- “Display Event Messages from `mwsamp` Control” on page 13-54

### More About

- “COM Event Handlers” on page 13-29

## Display Event Messages from mwsamp Control

This example shows how to handle events fired by the MATLAB ActiveX control, `mwsamp2`.

### Create Event Handler Routines

Create event handler files and save them to a folder on your path.

Create the `myclick.m` file.

```
function myclick(varargin)
disp('Single click function')
```

Create the `my2click.m` file.

```
function my2click(varargin)
disp('Double click function')
```

Create the `mymoused.m` file.

```
function mymoused(varargin)
disp('You have triggered the mouse down function')
disp('The X position is: ')
double(varargin{5})
disp('The Y position is: ')
double(varargin{6})
```

### Create Control and Register Events

Open a figure window.

```
f = figure('position', [100 200 200 200]);
```

Register the `Click` and `MouseDown` events.

```
ctrl = actxcontrol('mwsamp.mwsampctrl.2', [0 0 200 200], f, {'Click', 'myclick'; 'MouseDown', 'mymoused'})
```

### Respond to Control Events

When MATLAB creates the `mwsamp2` control, it also displays a figure window showing a label and circle at the center. If you click different positions in this window, you see a report in the MATLAB Command Window of the X and Y position of the mouse.

Each time you press the mouse button, the `MouseDown` event fires, calling the `mymoused` function. This function prints the position values for that event to the Command Window. For example:

```
The X position is:
ans =
    [122]
The Y position is:
ans =
    [63]
```

The `Click` event displays the `myclick` message.

```
Single click function
```

Double-clicking the mouse does nothing, since the `Db1Click` event is not registered.

### Register `Db1Click` Event

```
registerevent(ctrl1,{'Db1Click','my2click'})
```

When you double-click the mouse, MATLAB displays both the `myclick` and `my2click` messages.

```
Single click function
Double click function
```

### Display Control Events

Unregister the `Db1Click` event.

```
unregisterevent(ctrl1,{'Db1Click','my2click'})
```

Display the currently registered events.

```
eventlisteners(ctrl1)

ans =
    'click'          'myclick'
    'mousedown'    'mymoused'
```

### Unregister All Events

```
unregisterallevents(ctrl1)
eventlisteners(ctrl1)
```

```
ans =  
    {}
```

Clicking the mouse in the control window now does nothing since there are no active events.

Close the figure window.

### See Also

`actxcontrol` | `eventlisteners` | `registerevent` | `unregisterallevents`

### Related Examples

- “MATLAB Sample ActiveX Control `mwsamp`” on page 13-53

### More About

- “COM Event Handlers” on page 13-29



## Add Position Property to mwsamp Control

This example shows how to add a custom property, `Position` to the `mwsamp` control.

Create the control.

```
h = actxcontrol('mwsamp.mwsampctr1.2', [200 120 200 200]);
```

Create the property.

```
addproperty(h, 'Position')
```

Initialize the values.

```
h.Position = [200 120];
```

List the properties of the control.

```
get(h)
```

```
Label: 'Label'  
Radius: 20  
Ret_IDispatch: [1x1 Interface.mwsamp2_ActiveX_Control_module._DMwsamp2]  
Position: [200 120]
```

Property `Position` has been added.

### More About

- “Custom Properties” on page 13-23

## Save mwsamp2 COM Control

This example shows how to restore original `mwsamp2` control settings.

Create the `mwsamp2` control.

```
f = figure('position',[100 200 200 200]);  
h = actxcontrol('mwsamp.mwsampctrl1.2',[0 0 200 200],f);
```

Save the control settings to a new file, `mwsample`.

```
save(h,'mwsample')
```

Alter the figure by changing its label and the radius of the circle.

```
h.Label = 'Circle';  
h.Radius = 50;  
Redraw(h)
```

Restore the control to its original state.

```
load(h,'mwsample')
```

Verify the results.

```
get(h)
```

```
Label: 'Label'  
Radius: 20  
Ret_IDispatch: [1x1 Interface.mwsamp2_ActiveX_Control_module._DMwsamp2]
```

MATLAB displays the original settings.

### Related Examples

- “MATLAB Sample ActiveX Control `mwsamp`” on page 13-53
- “Display Event Messages from `mwsamp` Control” on page 13-54
- “Add Position Property to `mwsamp` Control” on page 13-57
- “Redraw Circle in `mwsamp` Control” on page 13-48

## Deploy ActiveX Controls Requiring Run-Time Licenses

### In this section...

“Create Function to Build Control” on page 13-59

“Build Control and License File” on page 13-59

“Build Executable” on page 13-60

“Deploy Files” on page 13-60

When you deploy a Microsoft ActiveX control that requires a run-time license, include a license key, which the control reads at run time. If the key matches the license key version of the control, an instance of the control is created. To deploy a run-time-licensed control with a MATLAB application, use the following procedure.

### Create Function to Build Control

Create a function, `buildcontrol.m`, to build the control. The file must contain two elements:

- The pragma `%%function actxlicense`. This pragma causes the MATLAB Compiler to embed a function named `actxlicense` into the standalone executable file you build.
- A call to `actxcontrol` to create an instance of the control.

Place this file in a folder outside of the MATLAB code tree.

Here is an example file:

```
function buildcontrol
%%function actxlicense
h=actxcontrol('MFCCONTROL2.MFCControl2Ctrl.1',[10 10 200 200]);
```

### Build Control and License File

Change to the folder where you placed the function you created to build the control. Call the function. When it executes this function, MATLAB determines whether the control requires a run-time license. If it does, MATLAB creates another file, named `actxlicense.m`, in the current working folder. The `actxlicense` function defined in this file provides the license key to MATLAB at run time.

## **Build Executable**

Call the MATLAB Compiler build function to create the standalone executable from the file you created to build the control. The executable contains both the function that builds the control and the `actxlicense` function.

```
mcc -m buildcontrol
```

## **Deploy Files**

Distribute `buildcontrol.exe`, `buildcontrol.ctf`, and the control (`.ocx` or `.dll`).

## **See Also**

`actxcontrol`

## Microsoft Forms 2.0 Controls

### In this section...

“Affected Controls” on page 13-61

“Replacement Controls” on page 13-61

Microsoft Forms 2.0 controls are designed for use with applications enabled by Microsoft Visual Basic for Applications (VBA). An example is Microsoft Office software.

If you encounter problems when creating or using Forms 2.0 controls, use the following replacement controls. Alternatively, consult article 236458 in the Microsoft Knowledge Base for further information.

### Affected Controls

- Forms.TextBox.1
- Forms.CheckBox.1
- Forms.CommandButton.1
- Forms.Image.1
- Forms.OptionButton.1
- Forms.ScrollBar.1
- Forms.SpinButton.1
- Forms.TabStrip.1
- Forms.ToggleButton.1

### Replacement Controls

Microsoft recommends the following replacements:

Old	New
Forms.TextBox.1	RICHTEXT.RichtextCtrl.1
Forms.CheckBox.1	vidtc3.Checkbox
Forms.CommandButton.1	MSComCtl2.FlatScrollBar.2
Forms.TabStrip.1	COMCTL.TabStrip.1

## **External Websites**

- Using Microsoft Forms 2.0 in Internet Explorer

## COM Collections

COM *collections* are a way to support groups of related COM objects that can be iterated over. A collection is itself an interface with a read-only `Count` property and an `Item` method to retrieve a single item from the collection.

The `Item` method is indexed, which means that it requires an argument that specifies which item in the collection is being requested. The data type of the index is a data type specified by the control or server that supports the collection. Although integer indices are common, the index could also be a text value. Often, the return value from the `Item` method is itself an interface. Like all interfaces, release this interface when you are finished with it.

This example iterates through the members of a collection. Each member of the collection is itself an interface (called `Plot` and represented by a MATLAB COM object called `hPlot`). In particular, this example iterates through a collection of `Plot` interfaces, invokes the `Redraw` method for each interface, and then releases each interface:

```
hCollection = hControl.Plots;
for i = 1:hCollection.Count
    hPlot = invoke(hCollection,'Item', i);
    Redraw(hPlot)
    release(hPlot);
end;
release(hCollection);
```

## MATLAB COM Support Limitations

Microsoft does not support loading 32-bit DLLs or in-process COM servers into a 64-bit application, or conversely. So you cannot use 32-bit DLL COM objects in 64-bit MATLAB.

Limitations of MATLAB COM support are:

- MATLAB does not support custom COM interfaces (IUnknown) with 64-bit MATLAB.
- MATLAB only supports indexed collections.
- COM controls are not printed with figure windows.
- “Unsupported Types” on page 13-15
- MATLAB does not support asynchronous events.
- A MATLAB COM ActiveX control container does not in-place activate controls until they are visible.



## Interpreting Argument Callouts in COM Error Messages

When a MATLAB client sends a command with an invalid argument to a COM server application, the server sends back an error message in the following format.

```
??? Error: Type mismatch, argument n.
```

If you do not use the dot syntax format, be careful interpreting the argument number in this message.

For example, using dot syntax, if you type:

```
handle.PutFullMatrix('a','base',7,[5 8]);
```

MATLAB displays:

```
??? Error: Type mismatch, argument 3.
```

In this case, the argument, 7, is invalid because `PutFullMatrix` expects the third argument to be an array data type, not a scalar. In this example, the error message identifies 7 as argument 3.

However, if you use the syntax:

```
PutFullMatrix(handle,'a','base',7,[5 8]);
```

MATLAB displays:

```
??? Error: Type mismatch, argument 3.
```

In this call to the `PutFullMatrix` function, 7 is argument four. However, the COM server does not receive the first argument. The `handle` argument merely identifies the server. It does not get passed to the server. The server reads 'a' as the first argument, and the invalid argument, 7, as the third.

### More About

- “COM Methods” on page 13-24



# MATLAB COM Automation Server Support

---

- “Register MATLAB as Automation Server” on page 14-2
- “MATLAB COM Automation Server Interface” on page 14-4
- “Create MATLAB Server” on page 14-7
- “Connect to Existing MATLAB Server” on page 14-9
- “MATLAB Application as DCOM Server” on page 14-10
- “VT\_DATE Data Type” on page 14-11
- “Data Types For Visual Basic .NET Clients” on page 14-12
- “Visible Property” on page 14-13
- “Shared or Dedicated Server” on page 14-14
- “Manually Create Automation Server” on page 14-15
- “Launch MATLAB as Automation Server in Desktop Mode” on page 14-16
- “Call MATLAB Function from Visual Basic .NET Client” on page 14-17
- “Pass Complex Data to MATLAB from C# Client” on page 14-18
- “Call MATLAB Function from C# Client” on page 14-20
- “View MATLAB Functions from Visual Basic .NET Object Browser” on page 14-22
- “Waiting for MATLAB Application to Complete” on page 14-23
- “Conversion of MATLAB Types to COM Types” on page 14-24
- “Conversion of COM Types to MATLAB Types” on page 14-26

## Register MATLAB as Automation Server

### In this section...

“When to Register MATLAB” on page 14-2

“Register from System Prompt” on page 14-2

“Register from MATLAB Command Prompt” on page 14-3

### When to Register MATLAB

To use MATLAB as an Automation server, you first must register the application in the Windows registry, which happens when you install a new version of MATLAB. If you have multiple versions of MATLAB installed on your system, only one version is registered. By default, this version is the last version you installed. This version remains registered until you manually change the registry, or install a new version.

To manually register MATLAB, choose one of these options:

- “Register from System Prompt” on page 14-2
- “Register from MATLAB Command Prompt” on page 14-3

You must have administrator privileges to change the Windows registry. Based on your User Account Control (UAC) settings, you might need to right-click the Windows Command Processor or the MATLAB icon and select **Run as administrator**. If that option is not available, contact your system administrator.

If MATLAB is unable to update the registry, it still displays a new minimized command window. Open this window and exit MATLAB.

### Register from System Prompt

To register MATLAB as an Automation server from the Windows system prompt, first open a Windows Command Processor using the **Run as administrator** option, if necessary.

Move to the folder containing the executable file for the MATLAB version you want.

```
cd matlabroot\bin\arch
```

If you do not use this folder, the `matlab` command starts the first instance of MATLAB on the system path.

```
matlab -regserver
```

MATLAB displays a minimized command window. Open this window and exit MATLAB.

## Register from MATLAB Command Prompt

To register MATLAB as an Automation server from within MATLAB, first start MATLAB, with the **Run as administrator** option, if necessary. Because you open MATLAB to run this command, you know what MATLAB version you will register.

```
regmatlabserver
```

MATLAB opens a minimized command window. Open this window and exit MATLAB.

## See Also

matlab (Windows)

## More About

- “Create MATLAB Server” on page 14-7

## MATLAB COM Automation Server Interface

### In this section...

“COM Server Types” on page 14-4

“Shared and Dedicated Servers” on page 14-4

“Programmatic Identifiers” on page 14-4

“In-Process and Out-of-Process Servers” on page 14-5

### COM Server Types

There are three types of COM servers:

- Automation — A server that supports the OLE Automation standard. Automation servers are based on the `IDispatch` interface. Clients of all types, including scripting clients, access Automation servers.
- Custom — A server that implements an interface directly derived from `IUnknown`. Custom servers are preferred when faster client access is critical.
- Dual — A server that implements a combination of Automation and Custom interfaces.

### Shared and Dedicated Servers

The MATLAB Automation server has two modes:

- Shared — One or more client applications connect to the same MATLAB server. All clients share server.
- Dedicated — Each client application creates its own dedicated MATLAB server.

If you use `matlab.application` as your ProgID, MATLAB creates a shared server. For more information, see “Shared or Dedicated Server” on page 14-14.

### Programmatic Identifiers

To create an instance of a COM object, you use its programmatic identifier, or *ProgID*. The ProgID is a unique string defined by the component vendor to identify the COM object. You obtain a ProgID from your vendor documentation.

The MATLAB ProgIDs for shared servers are:

- `Matlab.Application` — Starts a command window Automation server with the version of MATLAB that was most recently used as an Automation server (might not be the latest installed version of MATLAB).
- `Matlab.Autoserver` — Starts a command window Automation server using the most recent version of MATLAB.
- `Matlab.Desktop.Application` — Starts the full desktop MATLAB as an Automation server using the most recent version of MATLAB.

The ProgIDs for dedicated servers are:

- `Matlab.Application.Single`
- `Matlab.Autoserver.Single`

These version-independent MATLAB ProgIDs specify the currently installed and registered version of MATLAB.

In order to create an instance of a specific installed and registered MATLAB version, you can use a version-dependent ProgID. For example, using the ProgID `Matlab.Application.7.14` creates an instance of MATLAB version 7.14 (R2012a).

## **In-Process and Out-of-Process Servers**

You can configure a server three ways. MATLAB supports all of these configurations.

- “In-Process Server” on page 14-5
- “Local Out-of-Process Server” on page 14-5
- “Remote Out-of-Process Server” on page 14-6

### **In-Process Server**

An in-process server is a component implemented as a dynamic link library (DLL) or ActiveX control that runs in the same process as the client application, sharing address space. Communication between client and server is relatively fast and simple.

### **Local Out-of-Process Server**

A local out-of-process server is a component implemented as an executable (EXE) file that runs in a separate process from the client application. The client and server processes are

on the same computer system. This configuration is slower due to the overhead required when transferring data across process boundaries.

### **Remote Out-of-Process Server**

This is a type of out-of-process server; however, the client and server processes are on different systems and communicate over a network. Network communications, in addition to the overhead required for data transfer, can make this configuration slower than the local out-of-process configuration. This configuration runs only on systems that support the *Distributed Component Object Model (DCOM)*.



## Create MATLAB Server

### In this section...

“Getting Started” on page 14-7

“Get or Set the Status of a MATLAB Automation Server” on page 14-8

### Getting Started

To create a server, you need a programmatic identifier (ProgID) to identify the server. The ProgID for MATLAB is `matlab.application`. For a complete list, see “Programmatic Identifiers” on page 14-4.

How you create an Automation server depends on the controller you are using. Consult your controller's documentation for this information. Possible options include:

- Add this statement to a Visual Basic .NET application.  

```
MatLab = CreateObject("Matlab.Application")
```
- “Manually Create Automation Server” on page 14-15.
- Use the Visual Basic Object Browser to access methods.

### Access Methods from the Visual Basic Object Browser

You can use the Object Browser of your Visual Basic client application to see what methods are available from a MATLAB Automation server. To do this you need to reference the MATLAB *type library* in your Visual Basic project.

To set up your Visual Basic project:

- 1 Select the **Project** menu.
- 2 Select **Reference** from the subsequent menu.
- 3 Check the box next to the **MATLAB Application Type Library**.
- 4 Click **OK**.

In your Visual Basic code, use the `New` method to create the server:

```
Matlab = New MApp.MLApp
```

View MATLAB Automation methods from the Visual Basic Object Browser under the Library called `MLAPP`.

## Get or Set the Status of a MATLAB Automation Server

To make MATLAB an Automation server, use the `enableservice` function. For example, type:

```
enableservice('AutomationServer',true)
```

To determine the current state of a MATLAB Automation server, type:

```
enableservice('AutomationServer')
```

If MATLAB displays:

```
ans =  
    1
```

then MATLAB is currently an Automation server.

### See Also

`enableservice`

### Related Examples

- “Manually Create Automation Server” on page 14-15

### More About

- “Register MATLAB as Automation Server” on page 14-2
- “Programmatic Identifiers” on page 14-4
- “MATLAB Startup Folder”

## Connect to Existing MATLAB Server

It is not always necessary to create a new instance of a MATLAB server whenever your application needs some task done in MATLAB. Clients can connect to an existing MATLAB Automation server using the `actxGetRunningServer` function or by using a command similar to the Visual Basic `.NET GetObject` command.

### Using Visual Basic .NET Code

The Visual Basic `.NET` command shown here returns a handle `h` to the MATLAB server application:

```
h = GetObject(, "matlab.application")
```

---

**Note:** It is important to use the syntax shown above to connect to an existing MATLAB Automation server. Omit the first argument, and make sure the second argument is as shown.

---

The following Visual Basic `.NET` example connects to an existing MATLAB server, then executes a plot command in the server. If you do not already have a MATLAB server running, create one following the instructions in “Access Methods from the Visual Basic Object Browser” on page 14-7.

```
Dim h As Object
h = GetObject(, "matlab.application")

' Handle h should be valid now.
' Test it by calling Execute.
h.Execute ("plot([0 18], [7 23])")
```

## MATLAB Application as DCOM Server

Distributed Component Object Model (DCOM) is a protocol that allows COM connections to be established over a network. If you are using a version of the Windows operating system that supports DCOM and a controller that supports DCOM, you can use the controller to start a MATLAB server on a remote machine.

To do this, DCOM must be configured properly, and MATLAB must be installed on each machine that is used as a client or server. (Even though the client machine may not be running MATLAB in such a configuration, the client machine must have a MATLAB installation because certain MATLAB components are required to establish the remote connection.) Consult the DCOM documentation for how to configure DCOM for your environment.

### External Websites

- <http://www.mathworks.com/matlabcentral/answers/102255-how-can-i-make-a-dcom-server-instance-of-matlab-visible>
- <http://www.mathworks.com/matlabcentral/answers/95647-how-can-i-utilize-matlab-on-a-remote-machine-as-a-distributed-com-dcom-server>

## VT\_DATE Data Type

To pass a VT\_DATE type input to a Visual Basic program or an ActiveX control method, use the MATLAB class `COM.date`. For example:

```
d = COM.date(2005,12,21,15,30,05);  
get(d)  
    Value: 7.3267e+005  
    String: '12/21/2005 3:30:05 PM'
```

Use the `now` function to set the `Value` property to a date number:

```
d.Value = now;
```

`COM.date` accepts the same input arguments as `datetime`.

## Data Types For Visual Basic .NET Clients

Data types for the arguments and return values of the server functions are expressed as Automation data types, which are language-independent types defined by the Automation protocol.

For example, **BSTR** is a wide-character string type defined as an Automation type, and is the same data format used by the Visual Basic language to store strings. Any COM-compliant controller should support these data types, although the details of how you declare and manipulate these are controller specific.

## Visible Property

You have the option of making MATLAB visible or not by setting the `Visible` property. When visible, MATLAB appears on the desktop, enabling the user to interact with it. This might be useful for such purposes as debugging. When not visible, the MATLAB window does not appear, thus perhaps making for a cleaner interface and also preventing any interaction with the application.

By default, the `Visible` property is enabled, or set to 1. You can change the `Visible` property by setting it to 0 (invisible) or 1 (visible).

## Shared or Dedicated Server

You can start the MATLAB Automation server in one of two modes – shared or dedicated. A dedicated server is dedicated to a single client; a shared server is shared by multiple clients. The mode is determined by the programmatic identifier (ProgID) used by the client to start MATLAB.

### Starting a Shared Server

The ProgID, `matlab.application`, specifies the default mode, which is shared. You can also use the version-specific ProgID, `matlab.application.N.M`, where N is the major version and M is the minor version of your MATLAB. For example, use N = 7 and M = 4 for MATLAB version 7.4.

Once MATLAB is started as a shared server, all clients that request a connection to MATLAB using the shared server ProgID connect to the already running instance of MATLAB. In other words, there is never more than one instance of a shared server running, since it is shared by all clients that use the shared server ProgID.

### Starting a Dedicated Server

To specify a dedicated server, use the ProgID, `matlab.application.single`, (or the version-specific ProgID, `matlab.application.single.N.M`).

Each client that requests a connection to MATLAB using a dedicated ProgID creates a separate instance of MATLAB; it also requests the server not be shared with any other client. Therefore, there can be several instances of a dedicated server running simultaneously, since the dedicated server is not shared by multiple clients.




## Manually Create Automation Server

Microsoft Windows operating system automatically creates an Automation server when a controller application first establishes a server connection. Alternatively, you can manually create the server before starting any of the client processes.

To create a MATLAB server manually, use the `-automation` switch in the `matlab` startup command. From the operating system prompt, type:

```
matlab -automation
```

Alternatively, you can add this switch every time you run MATLAB, as follows:

- 1 Right-click the MATLAB shortcut icon  and select **Properties** from the context menu. The Properties dialog box for `matlab.exe` opens to the **Shortcut** tab.
- 2 In the **Target** field, add `-automation` to the end of the target path for `matlab.exe`. Be sure to include a space between the file name and the symbol `-`. For example:

```
"C:\Program Files\MATLAB\R2016a\bin\win64\MATLAB.exe -automation"
```

---

**Note:** When the operating system automatically creates a MATLAB server, it too uses the `-automation` switch. In this way, MATLAB servers are differentiated from other MATLAB sessions. This protects controllers from interfering with any interactive MATLAB sessions that might be running.

---

## Launch MATLAB as Automation Server in Desktop Mode

To launch MATLAB as a COM Automation server in full desktop mode, use the programmatic identifier `Matlab.Desktop.Application`. For example, in Microsoft Visual Basic .NET:

```
Dim MatLab As Object  
Dim Result As String  
MatLab = CreateObject("Matlab.Desktop.Application")  
Result = MatLab.Execute("surf(peaks)")
```

## Call MATLAB Function from Visual Basic .NET Client

This example calls a user-defined MATLAB function named `solve_bvp` from a Microsoft Visual Basic client application through a COM interface. It also plots a graph in a new MATLAB window and performs a simple computation:

```
Dim MatLab As Object
Dim Result As String
Dim MReal(1, 3) As Double
Dim MImag(1, 3) As Double

MatLab = CreateObject("Matlab.Application")

'Calling MATLAB function from VB
'Assuming solve_bvp exists at specified location
Result = MatLab.Execute("cd d:\matlab\work\bvp")
Result = MatLab.Execute("solve_bvp")

'Executing other MATLAB commands
Result = MatLab.Execute("surf(peaks)")
Result = MatLab.Execute("a = [1 2 3 4; 5 6 7 8]")
Result = MatLab.Execute("b = a + a ")
'Bring matrix b into VB program
MatLab.GetFullMatrix("b", "base", MReal, MImag)
```

## Pass Complex Data to MATLAB from C# Client

This example creates complex data in the client C# program and passes it to MATLAB. The matrix consists of a vector of real values in variable `pr` and of imaginary values in `pi`. The example reads the matrix back into the C# program.

The reference to the MATLAB Type Library for C# is:

```
MApp.MApp matlab = new MApp.MApp();
```

From your C# client program, add a reference to your project to the MATLAB COM object. For example, in Microsoft Visual Studio, open your project. From the **Project** menu, select **Add Reference**. Select the **COM** tab in the Add Reference dialog box. Select the MATLAB application.

Here is the complete example:

```
using System;
namespace ConsoleApplication4
{
class Class1
{
[STAThread]
static void Main(string[] args)
{
MApp.MApp matlab = new MApp.MApp();

System.Array pr = new double[4];
pr.SetValue(11,0);
pr.SetValue(12,1);
pr.SetValue(13,2);
pr.SetValue(14,3);

System.Array pi = new double[4];
pi.SetValue(1,0);
pi.SetValue(2,1);
pi.SetValue(3,2);
pi.SetValue(4,3);

matlab.PutFullMatrix("a", "base", pr, pi);

System.Array prresult = new double[4];
System.Array piresult = new double[4];
```

```
matlab.GetFullMatrix("a", "base", ref presult, ref piresult);  
}  
}  
}
```

### **See Also**

[GetFullMatrix](#) | [PutFullMatrix](#)

## Call MATLAB Function from C# Client

This example shows how to call a user-defined MATLAB function, `myfunc`, from a C# application.

Create a MATLAB function, `myfunc`, in the folder `c:\temp\example`.

```
function [x,y] = myfunc(a,b,c)
x = a + b;
y = sprintf('Hello %s',c);
```

Create the C# application.

```
using System;
using System.Collections.Generic;
using System.Text;

namespace ConsoleApplication2
{
    class Program
    {
        static void Main(string[] args)
        {
            // Create the MATLAB instance
            MLab.MLab matlab = new MLab.MLab();

            // Change to the directory where the function is located
            matlab.Execute(@"cd c:\temp\example");

            // Define the output
            object result = null;

            // Call the MATLAB function myfunc
            matlab.Feval("myfunc", 2, out result, 3.14, 42.0, "world");

            // Display result
            object[] res = result as object[];

            Console.WriteLine(res[0]);
            Console.WriteLine(res[1]);
            Console.ReadLine();
        }
    }
}
```

In Microsoft Visual Studio, add a reference to your *C#* project to the MATLAB COM object. From the **Project** menu, select **Add Reference**.

Select the **COM** tab in the Add Reference dialog box.

Select the MATLAB application.

## View MATLAB Functions from Visual Basic .NET Object Browser

You can find out what methods are available from a MATLAB Automation server using the Object Browser of your Microsoft Visual Basic client application. To do this, follow this procedure in the client application to reference the MATLAB Application Type Library:

- 1 Select the **Project** menu.
- 2 Select **Reference** from the subsequent menu.
- 3 Check the box next to the **MATLAB Application Type Library**.
- 4 Click **OK**.

This enables you to view MATLAB Automation methods from the Visual Basic Object Browser under the Library called MLAPP. You can also see a list of MATLAB Automation methods when you use the term `Matlab` followed by a period. For example:

```
Dim Matlab As MApp.MApp
Private Sub View_Methods()
Matlab = New MApp.MApp
'The next line shows a list of MATLAB Automation methods
Matlab.
End Sub
```



## Waiting for MATLAB Application to Complete

When you call a MATLAB function from another program, the program might display a timeout message while waiting for the MATLAB function to complete. Refer to solutions posted in MATLAB Answers™ for tips for handling alerts from other programming languages.

### External Websites

- Why does Microsoft Excel generate the message "Microsoft Excel is waiting for another application to complete an OLE action." when I use Spreadsheet Link EX?
- Server Busy: Matlab called from Visual Basic (VB, VBA)

## Conversion of MATLAB Types to COM Types

<b>In this section...</b>
“Variant Data” on page 14-25
“SAFEARRAY Data” on page 14-25

The following table shows how MATLAB converts data from MATLAB to COM types.

<b>MATLAB Type</b>	<b>Closest COM Type</b>	<b>Allowed Types</b>
handle	VT_DISPATCH VT_UNKNOWN	VT_DISPATCH VT_UNKNOWN
character vector	VT_BSTR	VT_LPWSTR VT_LPSTR VT_BSTR VT_FILETIME VT_ERROR VT_DECIMAL VT_CLSID VT_DATE
int16	VT_I2	VT_I2
uint16	VT_UI2	VT_UI2
int32	VT_I4	VT_I4 VT_INT
uint32	VT_UI4	VT_UI4 VT_UINT
int64	VT_I8	VT_I8
uint64	VT_UI8	VT_UI8
single	VT_R4	VT_R4
double	VT_R8	VT_R8 VT_CY
logical	VT_BOOL	VT_BOOL
char	VT_I1	VT_I1 VT_UI1

## Variant Data

`variant` is any data type except a structure or a sparse array. (For more information, see “Fundamental MATLAB Classes”.)

When used as an input argument, MATLAB treats `variant` and `variant(pointer)` the same way.

If you pass an empty array (`[]`) of type `double`, MATLAB creates a `variant(pointer)` set to `VT_EMPTY`. Passing an empty array of any other numeric type is not supported.

MATLAB Argument	Closest COM Type	Allowed Types
<code>variant</code>	<code>VT_VARIANT</code>	<code>VT_VARIANT</code> <code>VT_USERDEFINED</code> <code>VT_ARRAY</code>
<code>variant(pointer)</code>	<code>VT_VARIANT</code>	<code>VT_VARIANT</code>   <code>VT_BYREF</code>

## SAFEARRAY Data

When a COM method identifies a `SAFEARRAY` or `SAFEARRAY(pointer)`, the MATLAB equivalent is a matrix.

MATLAB Argument	Closest COM Type	Allowed Types
<code>SAFEARRAY</code>	<code>VT_SAFEARRAY</code>	<code>VT_SAFEARRAY</code>
<code>SAFEARRAY(pointer)</code>	<code>VT_SAFEARRAY</code>	<code>VT_SAFEARRAY</code>   <code>VT_BYREF</code>

## See Also

`GetWorkspaceData`

## Conversion of COM Types to MATLAB Types

The following table shows how MATLAB converts data from a COM application into MATLAB types.

COM Variant Type	Description	MATLAB Type
VT_DISPATCH VT_UNKNOWN	IDispatch * IUnknown * MATLAB does not support the IUnknown and IDispatch interfaces with 64-bit MATLAB.	handle
VT_LPWSTR VT_LPSTR VT_BSTR VT_FILETIME VT_ERROR VT_DECIMAL VT_CLSID VT_DATE	wide null terminated string null terminated string OLE Automation string FILETIME SCODE 16-byte fixed point Class ID date	character vector
VT_INT VT_UINT VT_I2 VT_UI2 VT_I4 VT_UI4 VT_R4 VT_R8 VT_CY	signed machine int unsigned machine int 2 byte signed int unsigned short 4 byte signed int unsigned long 4 byte real 8 byte real currency	double
VT_I8	signed int64	int64
VT_UI8	unsigned int64	uint64
VT_BOOL		logical
VT_I1 VT_UI1	signed char unsigned char	char
VT_VARIANT	VARIANT *	variant

COM Variant Type	Description	MATLAB Type
VT_USERDEFINED VT_ARRAY	user-defined type SAFEARRAY*	
VT_VARIANT   VT_BYREF	VARIANT * void* for local use	variant(pointer)
VT_SAFEARRAY	use VT_ARRAY in VARIANT	SAFEARRAY
VT_SAFEARRAY   VT_BYREF		SAFEARRAY(pointer)

### See Also

PutWorkspaceData



# Using Web Services with MATLAB

---

- “Send and Receive HTTP Messages” on page 15-2
- “What Is the HTTP Interface?” on page 15-5
- “Manage Cookies” on page 15-6
- “RequestMessage complete method” on page 15-8
- “HTTP Data Type Conversion” on page 15-9
- “Display Progress Monitor for HTTP Message” on page 15-17
- “Set Up WSDL Tools” on page 15-21
- “Display a World Map” on page 15-22
- “Using WSDL Web Service with MATLAB” on page 15-27
- “Access Services That Use WSDL Documents” on page 15-29
- “Error Handling” on page 15-31
- “XML-MATLAB Data Type Conversion” on page 15-33
- “Limitations to WSDL Document Support” on page 15-35

## Send and Receive HTTP Messages

This example shows how to send a request to a server that involves redirection and might require digest authentication.

The `sendRequest` function automatically redirects and authenticates on the first request. For subsequent requests, you do not want to pay the cost of a redirect. To do this, `sendRequest` saves the cookies received on previous requests and reuses them for subsequent requests.

`sendRequest` illustrates the use of the history, the reuse of a custom `HTTPOptions` object to change the default timeout, and the use of saved credentials.

This example does not illustrate a robust, general-purpose mechanism for achieving these results. In particular, `sendRequest` returns all cookies received from a host in every subsequent message to that host, regardless of the domain, path, expiration, or other properties. `sendRequest` also does not save credentials or cookies across MATLAB sessions. Nonetheless, `sendRequest` is adequate for many applications.

Create the `sendRequest` function from the following code.

```
function response = sendRequest(uri,request)

% uri: matlab.net.URI
% request: matlab.net.http.RequestMessage
% response: matlab.net.http.ResponseMessage

% matlab.net.http.HTTPOptions persists across requests to reuse previous
% Credentials in it for subsequent authentications
persistent options

% infos is a containers.Map object where:
%   key is uri.Host;
%   value is "info" struct containing:
%       cookies: vector of matlab.net.http.Cookie or empty
%       uri: target matlab.net.URI if redirect, or empty
persistent infos

if isempty(options)
    options = matlab.net.http.HTTPOptions('ConnectTimeout',20);
end

if isempty(infos)
```



```

        infos = containers.Map;
    end
    host = string(uri.Host); % get Host from URI
    try
        % get info struct for host in map
        info = infos(host);
        if ~isempty(info.uri)
            % If it has a uri field, it means a redirect previously
            % took place, so replace requested URI with redirect URI.
            uri = info.uri;
        end
        if ~isempty(info.cookies)
            % If it has cookies, it means we previously received cookies from this host.
            % Add Cookie header field containing all of them.
            request = request.addFields(matlab.net.http.field.CookieField(info.cookies));
        end
    catch
        % no previous redirect or cookies for this host
        info = [];
    end

    % Send request and get response and history of transaction.
    [response, ~, history] = request.send(uri, options);
    if response.StatusCode ~= matlab.net.http.StatusCode.OK
        return
    end

    % Get the Set-Cookie header fields from response message in
    % each history record and save them in the map.
    arrayfun(@addCookies, history);

    % If the last URI in the history is different from the URI sent in the original
    % request, then this was a redirect. Save the new target URI in the host info struct.
    targetURI = history(end).URI;
    if ~isequal(targetURI, uri)
        if isempty(info)
            % no previous info for this host in map; create new one
            infos(char(host)) = struct('cookies',[],'uri',targetURI);
        else
            % change URI in info for this host and put it back in map
            info.uri = targetURI;
            infos(char(host)) = info;
        end
    end
end

```

```
function addCookies(record)
    % Add cookies in Response message in history record
    % to the map entry for the host to which the request was directed.
    %
    ahost = record.URI.Host; % the host the request was sent to
    cookieFields = record.Response.getFields('Set-Cookie');
    if isempty(cookieFields)
        return
    end
    cookieData = cookieFields.convert(); % get array of Set-Cookie structs
    cookies = [cookieData.Cookie]; % get array of Cookies from all structs
    try
        % If info for this host was already in the map, add its cookies to it.
        ainfo = infos(ahost);
        ainfo.cookies = [ainfo.cookies cookies];
        infos(char(ahost)) = ainfo;
    catch
        % Not yet in map, so add new info struct.
        infos(char(ahost)) = struct('cookies',cookies,'uri',[]);
    end
end
end
```

Call the function.

```
request = matlab.net.http.RequestMessage;
uri = matlab.net.URI('http://www.mathworks.com/products');
response = sendRequest(uri,request)
```

response = ResponseMessage with properties:

```
StatusLine: 'HTTP/1.1 200 OK'
StatusCode: OK
Header: [1×11 matlab.net.http.HeaderField]
Body: [1×1 matlab.net.http.MessageBody]
Completed: 0
```

Your response values might be different.

## See Also

CookieField | HTTPOptions | LogRecord | Message.addFields | RequestMessage.send | ResponseMessage | URI

## What Is the HTTP Interface?

The MATLAB HTTP Interface is an API that provides functionality to issue properly structured HTTP requests and process their responses. You can also use the RESTful web services functions, `webread` and `webwrite`, to make HTTP requests. However, some interactions with a web service are more complex and require functionality not supported by these functions.

The HTTP Interface API is designed for programmatic use in scripts and functions. The API is an object model for HTTP data structures. It includes classes for messages, their headers and fields, and other entities defined in the Internet Engineering Task Force (IETF®) standards. For more information, see the Request for Comments (RFC) documents 7230, 7231, 7235, 2617 and 6265. The API contains functions that implement semantics of HTTP messaging and utilities for processing the data sent and received. It also contains support classes required to process, transmit, and receive messages.

The API is based on the HTTP/1.1 protocol.

### More About

- “Web Access”

### External Websites

- The Internet Engineering Task Force (IETF®)

## Manage Cookies

The HTTP interface provides classes for you to manage cookies in HTTP messages. For information about cookies, see RFC 6265 HTTP State Management Mechanism.

The `Cookie` class contains the name and value of the cookie. For example, display the properties of a `Cookie` object `C`.

```
C =  
Cookie with properties:  
  
    Name: "JSESSIONID"  
    Value: "688412d8ed1cdf15f4a736dc6ab3"
```

The `CookieInfo` class contains the cookie, as well as its attributes. The attributes are the properties of the `CookieInfo` object. For example, `info` is a `CookieInfo` object containing cookie `C`.

```
class(info)  
  
ans = matlab.net.http.CookieInfo
```

Display attributes of the cookie.

```
info.Expires  
  
ans =  
    Sun, 26 Mar 2084 17:15:30 GMT  
  
info.CreationTime  
  
ans =  
    Tue, 07 Jun 2016 09:38:56 GMT
```

A server returns cookies in a response message using a `SetCookieField` object. To get a `CookieInfo` object, call the `SetCookieField.convert` method.

To send a cookie to the server, add a `CookieField` object to a request message.

### See Also

[matlab.net.http.field.SetCookieField.convert](#) | [matlab.net.http.field.SetCookieField](#) | [matlab.net.http.field.CookieField](#) | [matlab.net.http.Cookie](#) | [matlab.net.http.CookieInfo](#)

## **External Websites**

- RFC 6265 HTTP State Management Mechanism

## RequestMessage complete method

- Use this function to determine whether the request is valid, and to see the request before sending it, including any conversion of `Body.Data` to `Body.Payload`. The returned `completedrequest` has the `Completed` property set to `true` and is suitable for sending without further alteration or processing. If you set the `request.Body.Data` property, `completedrequest.Body.Payload` is set to the converted `Data` property.
- For filling in and validating the `Header` and `RequestLine`, this method ignores the `Completed` property in `request`. It returns a modified `completedrequest` or errors if the `request` was not completed. Use this to determine whether a "manually" completed request is valid.
- If `Completed` is not set, this method always converts any `Data` in `request.Body` and stores the result in `completedrequest.Body.Payload`, overwriting any previous contents of `Payload`. As a result, both `Data` and `Payload` in the `completedrequest.Body` property contain data. This is different from the behavior of `send` which does not save the `Payload` unless `HTTPOptions.SavePayload` is set. Take this memory usage and conversion time into account if the message contains a large amount of data.

### See Also

`matlab.net.http.RequestMessage.complete`

## HTTP Data Type Conversion

### In this section...

“Converting Data in Request Messages” on page 15-9

“Converting Data in Response Messages” on page 15-13

“Supported Image Data Subtypes” on page 15-15

The MATLAB HTTP interface API automatically converts data types used in HTTP messages to and from MATLAB types.

### Converting Data in Request Messages

When sending a message with a payload, assign your MATLAB data to the `MessageBody.Data` property, then send it as a `RequestMessage.Body` property. The type of your MATLAB data depends on the HTTP Content-Type of the message. If you do not specify a Content-Type, then MATLAB assumes Content-Type values, as described in “Content-Type Not Specified” on page 15-11.

This table shows how MATLAB converts `Data` to a payload in a request message based on the type/subtype properties and the charset attribute that you specify in the Content-Type header field. The asterisk character (\*) means any subtype.

Content-Type	MATLAB Type in <code>MessageBody.Data</code> Property
<code>application/json</code>	<p><code>Data</code> converted to a Unicode value using the <code>jsonencode</code> function. MATLAB then uses the <code>unicode2native</code> function to convert the value to <code>uint8</code>, based on the charset attribute in the Content-Type header field.</p> <p>If you already have JSON-encoded text, then assign the text to the <code>Payload</code> property instead of the <code>Data</code> property. MATLAB converts the value to <code>uint8</code> using the charset attribute.</p> <p>If the charset attribute is not specified, then the default charset value is UTF-8.</p>
<code>text/*</code> for any subtype other than <code>csv</code> or <code>xml</code>	<p>If <code>Data</code> is a character or string array or a cell array of character vectors, MATLAB reshapes and concatenates the text by row to form a vector.</p>

Content-Type	MATLAB Type in <code>MessageBody.Data</code> Property
	<p>If <code>Data</code> is any other type, MATLAB converts <code>Data</code> using the <code>string</code> function. The resulting string is converted to <code>uint8</code> based on the charset.</p> <p>If you did not specify a charset, the default depends on the subtype. For the following subtypes, the default is UTF-8:</p> <ul style="list-style-type: none"> <li>• json</li> <li>• jtml</li> <li>• javascript</li> <li>• css</li> <li>• calendar</li> </ul> <p>For all other subtypes, MATLAB determines the charset. If all characters are in the ASCII range, then the charset is US-ASCII. Otherwise, the charset is UTF-8.</p> <hr/> <p><b>Note:</b> Servers might not properly interpret text types encoded as UTF-8 without an explicit UTF-8 charset. For best results, explicitly specify UTF-8 if your data contains non-ASCII characters.</p>
image/*	<p><code>Data</code> must be image data in a form acceptable to the <code>imwrite</code> function. Conversion of <code>Data</code> to <code>uint8</code> depends on the subtype. For information about supported types and for controlling the conversion, see “Supported Image Data Subtypes” on page 15-15.</p>
<ul style="list-style-type: none"> <li>• application/xml</li> <li>• text/xml</li> </ul>	<p>If <code>Data</code> is an XML DOM in the form of a Java <code>org.w3c.dom.Document</code> object, MATLAB converts it using the <code>xmlwrite</code> function.</p> <p>If <code>Data</code> is a string or character vector, MATLAB converts it to <code>uint8</code> using the specified charset. If not specified, the default charset value is UTF-8.</p>



Content-Type	MATLAB Type in <code>MessageBody.Data</code> Property
<p><code>audio/*</code></p>	<p>Data must audio data in a form acceptable to the <code>audiowrite</code> function. Create a cell array containing an m-by-n matrix of audio data and a sampling rate in Hz. You can specify additional arguments to <code>audiowrite</code> by adding name-value pair arguments to the cell array.</p> <p>MATLAB supports the following audio types:</p> <ul style="list-style-type: none"> <li>• <code>audio/x-wav</code></li> <li>• <code>audio/wav</code></li> <li>• <code>audio/mp4</code></li> <li>• <code>audio/vnd.wav</code></li> <li>• <code>application/ogg</code></li> <li>• <code>audio/flac</code></li> </ul>
<ul style="list-style-type: none"> <li>• <code>application/csv</code></li> <li>• <code>text/csv</code></li> <li>• <code>application/vnd.openxmlformats-officedocument.spreadsheetml.sheet</code></li> <li>• <code>application/vnd.ms-excel</code></li> </ul>	<p>Data must be a table in a form suitable for the <code>writetable</code> function.</p> <p>For <code>csv</code> subtypes, MATLAB converts <code>Data</code> to comma-delimited text using the specified charset. The default charset is US-ASCII.</p> <p>For the other types, MATLAB converts <code>Data</code> to Excel spreadsheet data.</p> <p>To specify additional name-value pair arguments to <code>writetable</code>, create a cell array containing <code>Data</code> and the additional arguments. If you specify a <code>'FileType'</code> argument, that type must be consistent with the subtype you specify.</p>

### Content-Type Not Specified

If you do not specify a `Content-Type` field in the request message, MATLAB assigns the type, subtype, and charset based on the type of the `Data` property. This assumed behavior might not result in the `Content-Type` you intended, or might fail to determine the type, so for best results, specify the `Content-Type`. The following table describes

the assumed Content-Type based on Data. Types not listed might be handled, but the behavior for unlisted types is not guaranteed to remain the same in future releases.

MessageBody.Data Property Type Content-Type Not Specified	Resulting Content-Type
string character array cell array of character vectors	text/plain
table	text/csv
cell vector whose first element is a table	text/csv — If FileType is csv, then there is a name,value pair in the vector with the value 'FileType', 'csv' or there is no such pair.  application/vnd.openxmlformats-officedocument.spreadsheetml.sheet — If FileType is spreadsheet.
org.w3c.dom.Document	application/xml
uint8 vector	To send a uint8 vector without conversion and ignoring the Content-Type header field, set the Payload property instead of Data.  To send character-based data with no conversion, use the unicode2native function. This function uses the charset attribute to convert Data to a uint8 vector.

If the type is not one of those listed above, then MATLAB determines whether it is one of the following character-based types:

- text/\*
- any type with a charset
- application/\*javascript
- application/x-www-form-urlencoded
- application/vnd.wolfram.mathematica.package

MATLAB converts these types to a string, using the charset, if specified, or US-ASCII for text/plain, UTF-8 for the application types, and the default MATLAB encoding for the other types.

## Converting Data in Response Messages

When receiving a message with a payload, MATLAB converts the incoming byte stream (`MessageBody.Data` property) to an appropriate MATLAB type.

The following table is a list of the Content-Types that MATLAB recognizes in a response message, based the type/subtype properties and the charset attribute in the received Content-Type field. MATLAB converts the data only if the `HTTPOptions.ConvertResponse` property is true, which is the default. In the table, the asterisk character (\*) means any characters.

Response Message Content-Type	MATLAB Type in <code>MessageBody.Data</code> Property
<code>application/json</code>	<code>Data</code> is converted to a string based on the charset and then to MATLAB data using the <code>jsondecode</code> function.
<code>image/*</code>	<p><code>Data</code> is converted to an image using the <code>imread</code> function with the specified subtype as the format, using default arguments. If <code>imread</code> returns more than one value, then <code>Data</code> is a cell array.</p> <p>For the supported types of image data, see “Supported Image Data Subtypes” on page 15-15. If the subtype is not in this list, then the subtype is passed to <code>imwrite</code> as the format, which might or might not be supported.</p> <p>To control the conversion of your image data or to override the type of conversion based on the subtype, specify additional arguments to <code>imwrite</code> using a cell array. If you specify an image format argument (<code>fmt</code>), then it overrides the default conversion.</p> <p>For example, the following code converts <code>imageData</code> to JPEG with compression quality 50 and sends the data to the</p>

Response Message Content-Type	MATLAB Type in MessageBody.Data Property
	<p>specified url with Content-Type set to image/jpeg.</p> <pre>body = MessageBody({imageData,'jpg','Quality',50}; req = RequestMessage('put',ContentTypeField('image/jpeg')); resp = req.send(url);</pre>
audio/*	<p>Data is converted using the <code>audioread</code> function to a cell array of two values, an m-by-n matrix of audio data and a sampling rate in Hz. The subtype determines the format used by <code>audioread</code>. The supported types are:</p> <ul style="list-style-type: none"> <li>• audio/wav</li> <li>• audio/x-wav</li> <li>• audio/vnd.wav</li> <li>• audio/mp4</li> <li>• audio/flac</li> </ul> <p><code>application/ogg</code> is not converted because ogg data does not necessarily contain audio only.</p>
text/csv text/comma-separated-values application/csv application/comma-separated-values	<p>Data is converted to a table using <code>readtable</code>, with assumed 'FileType' of csv and charset, if specified, or the MATLAB default encoding.</p>
application/*spreadsheet*	<p>Data is converted to a table using <code>readtable</code>, with 'FileType' assumed to be 'spreadsheet'.</p>
text/xml application/xml	<p>If Java is available, Data is converted to a Java <code>org.w3c.dom.Document</code> using the <code>xmlread</code> function.</p> <p>If Java is not available, Data is processed as <code>text/plain</code> with the UTF-8 charset.</p>

If the type is not one of those listed above, then MATLAB determines whether it is one of the following character-based types:

- `text/*`
- any type with a charset
- `application/*javascript`
- `application/x-www-form-urlencoded`
- `application/vnd.wolfram.mathematica.package`

MATLAB converts these types to a string, using the charset, if specified, or US-ASCII for `text/plain`, UTF-8 for the application types, and the default MATLAB encoding for the other types.

If MATLAB does not support the type, or if the `HTTPOptions.ConvertResponse` property is set to `false`, then:

- If the type is character-based, then `Data` contains the payload converted to string.
- Otherwise, `Data` contains the raw `uint8` vector.

If conversion of incoming data is attempted but fails (for example, `image/jpeg` data is not valid JPEG data), then the `History` property in the `HTTPException` thrown by the `RequestMessage.send` method contains the `ResponseMessage` with the `Payload` property set to the `uint8` payload and, if the type is character-based as listed above, then `Data` is set to the payload converted to a string.

## Supported Image Data Subtypes

The following subtypes are supported by the `imwrite` function as the specified format. For example, the format argument for subtype `bmp` is `'bmp'`. The `imread` function converts the data with the specified subtype as the format.

Subtype	Format Used by <code>imwrite</code> and <code>imread</code>
<code>bmp</code>	<code>'bmp'</code>
<code>gif</code>	<code>'gif'</code>
<code>jpeg</code>	<code>'jpeg'</code>
<code>jp2</code>	<code>'jp2'</code>

Subtype	Format Used by imwrite and imread
jpx	'jpx'
png	'png'
tiff	'tiff'
x-hdf	'hdf'
x-portable-bitmap	'pbm'
x-pcx	'pcx'
x-portable-graymap	'pgm'
x-portable-anymap	'pnm'
x-portable-pixmap	'ppm'
x-cmu-raster	'ras'
x-xwd	'xwd'

### See Also

`audioread` | `audiowrite` | `ContentTypeField` | `HTTPException` | `HTTPOptions` | `imread` | `imwrite` | `jsondecode` | `jsonencode` | `MessageBody` | `RequestMessage` | `ResponseMessage` | `xmlread` | `xmlwrite`

## Display Progress Monitor for HTTP Message

This example shows how to implement a progress monitor, `MyProgressMonitor`, that displays a progress bar for data transferred to and from a web site. The monitor displays a progress bar in a window created by the MATLAB `waitbar` function. It uses `set.Direction` and `set.Value` methods to monitor changes to the `Direction` and `Value` properties.

Each time MATLAB sets the `Direction` property, `MyProgressMonitor` creates a progress bar window and displays either a sending or a receiving message.

Create the following `MyProgressMonitor` class file.

The class initializes the `Interval` property to `.001` seconds because the example sends only 1MB of data. The small interval allows you to observe the progress bar.

```
classdef MyProgressMonitor < matlab.net.http.ProgressMonitor
    properties
        ProgHandle
        Direction matlab.net.http.MessageType
        Value uint64
        NewDir matlab.net.http.MessageType = matlab.net.http.MessageType.Request
    end

    methods
        function obj = MyProgressMonitor
            obj.Interval = .001;
        end

        function done(obj)
            obj.closeit();
        end

        function delete(obj)
            obj.closeit();
        end

        function set.Direction(obj, dir)
            obj.Direction = dir;
            obj.changeDir();
        end

        function set.Value(obj, value)
            obj.Value = value;
        end
    end
end
```

```
        obj.update();
    end
end

methods (Access = private)
function update(obj,~)
    % called when Value is set
    import matlab.net.http.*
    if ~isempty(obj.Value)
        if isempty(obj.Max)
            % no maximum means we don't know length, so message changes on
            % every call
            value = 0;
            if obj.Direction == MessageType.Request
                msg = sprintf('Sent %d bytes...', obj.Value);
            else
                msg = sprintf('Received %d bytes...', obj.Value);
            end
        else
            % maximum known; update proportional value
            value = double(obj.Value)/double(obj.Max);
            if obj.NewDir == MessageType.Request
                % message changes only on change of direction
                if obj.Direction == MessageType.Request
                    msg = 'Sending...';
                else
                    msg = 'Receiving...';
                end
            end
        end
    end
    if isempty(obj.ProgHandle)
        % if we don't have a progress bar, display it for first time
        obj.ProgHandle = ...
            waitbar(value, msg, 'CreateCancelBtn', @(~,~)cancelAndClose(obj));
        obj.NewDir = MessageType.Response;
    elseif obj.NewDir == MessageType.Request || isempty(obj.Max)
        % on change of direction or if no maximum known, change message
        waitbar(value, obj.ProgHandle, msg);
        obj.NewDir = MessageType.Response;
    else
        % no direction change else just update proportional value
        waitbar(value, obj.ProgHandle);
    end
end
end
```



```

function cancelAndClose(obj)
    % Call the required CancelFcn and then close our progress bar. This is
    % called when user clicks cancel or closes the window.
    obj.CancelFcn();
    obj.closeit();
end
end

function changeDir(obj,~)
    % Called when Direction is set or changed. Leave the progress bar display
    obj.NewDir = matlab.net.http.MessageType.Request;
end
end

methods (Access=private)
function closeit(obj)
    % Close the progress bar by deleting the handle so CloseRequestFcn isn't
    % called, because waitbar calls cancelAndClose(), which would cause
    % recursion.
    if ~isempty(obj.ProgHandle)
        delete(obj.ProgHandle);
        obj.ProgHandle = [];
    end
end
end
end
end

```

To start the operation, specify the progress monitor.

```

opt = matlab.net.http.HTTPOptions(...
    'ProgressMonitorFcn',@MyProgressMonitor,...
    'UseProgressMonitor',true);

```

Create the data.

```

x = ones(1000000,1,'uint8');
body = matlab.net.http.MessageBody(x);

```

Create the message. The `httpbin.org/put` service returns data received in a PUT message.

```

url = matlab.net.URI('http://httpbin.org/put');
method = matlab.net.http.RequestMethod.PUT;
req = matlab.net.http.RequestMessage(method,[],body);

```

Send the message.

```
[resp,~,hist] = req.send(url,opt);
```

### **See Also**

ProgressMonitor | waitfor

## Set Up WSDL Tools

This example shows how to find information to install the programs required to use a WSDL Web service in MATLAB. You need supported versions of the Oracle® Java JDK and the Apache™ CXF programs. While the programs are available at no charge, they require several hundred megabytes of disk space.

- Download and install the JDK software from the Java SE Downloads Web page. Use Java SE version 7u75.
- Download and install Apache CXF software from the Apache CXF Web page. Choose the latest release of version 2.7.
- Make note of the installation folders created by these programs. Set the paths to the these variables, `jdk = 'YOUR_JDK_PATH'` and `cxf = 'YOUR_CXF_PATH'`, then call:

```
matlab.wsd1.setWSDLToolPath('JDK',jdk,'CXF',cxf)
```

### See Also

`matlab.wsd1.setWSDLToolPath`

### External Websites

- <http://www.oracle.com/technetwork/java/javase/downloads>
- <http://cxf.apache.org/download>

## Display a World Map

This example shows how to access imagery from the United States Geological Survey (USGS) National Map SOAP server. To create the map, you need the following information.

- Get a map tile.
- Get the map name.
- Get the format of the tiles.

This example shows you how to call functions in the USGS Web service, `USGSImageryOnly_MapServer`, to get this information.

You must install the Java JDK and Apache CXF programs and set the tool paths to run this example.

```
p = matlab.wsd1.setWSDLToolPath;
if (isempty(p.JDK) || isempty(p.CXF))
    disp('Install the Java Development Kit (JDK) and Apache CXF programs.')
    disp('See the Set Up WSDL Tools link at the end of this example.')
else
    disp('Paths set to:')
    matlab.wsd1.setWSDLToolPath
end
```

Change your current folder to a writable folder.

Assign the WSDL URL.

```
wsd1File = ...
'http://basemap.nationalmap.gov/arcgis/services/USGSImageryOnly/MapServer?wsdl';
```

Create the class files for the client.

```
matlab.wsd1.createWSDLCient(wsd1File)
```

```
Created USGSImageryOnly_MapServer.
.\USGSImageryOnly_MapServer.m
.\+wsdl
```

In order to use `USGSImageryOnly_MapServer`, you must run `javaaddpath('.\+wsdl\mapserver`

```
ans =
```

```
@USGSImageryOnly_MapServer
```

Add the jar files to the Java path.

```
javaaddpath( './+wsdl\mapserver.jar' )
```

Start the service.

```
wsdl = USGSImageryOnly_MapServer;
```

Explore the service.

```
help USGSImageryOnly_MapServer
```

```
USGSImageryOnly_MapServer  A client to connect to the USGSImageryOnly_MapServer service
SERVICE = USGSImageryOnly_MapServer  connects to http://basemap.nationalmap.gov/arcgis
```

To communicate with the service, call a function on the SERVICE:

```
[...] = FUNCTION(SERVICE,arg,...)
```

See doc USGSImageryOnly\_MapServer for a list of functions.

Click the link [doc USGSImageryOnly\\_MapServer](#). MATLAB opens a reference page for USGSImageryOnly\_MapServer in the Help browser.

Read the documentation for the required inputs to the `GetMapTile` function.

```
help GetMapTile
```

```
--- help for USGSImageryOnly_MapServer/GetMapTile ---

GetMapTile
Result = GetMapTile(obj,MapName,Level,Row,Column,Format)
Inputs:
  obj - USGSImageryOnly_MapServer object
  MapName - string
  Level - numeric scalar (XML int)
  Row - numeric scalar (XML int)
  Column - numeric scalar (XML int)
  Format - string
Output:
  Result - vector of numbers 0-255 (XML base64Binary)
```

See also `USGSImageryOnly_MapServer`.

You need `MapName`, `Level`, `Row`, `Column`, and `Format` input arguments.

Read the documentation for a function that provides a map name, `GetDefaultMapName`.

help `GetDefaultMapName`

```
--- help for USGSImageryOnly_MapServer/GetDefaultMapName ---
```

```
GetDefaultMapName
```

```
Result = GetDefaultMapName(obj)
```

```
Inputs:
```

```
obj - USGSImageryOnly_MapServer object
```

```
Output:
```

```
Result - string
```

See also `USGSImageryOnly_MapServer`.

This function provides a map name.

Read the documentation for a function that provides a map format information, `GetTileImageInfo`.

help `GetTileImageInfo`

```
--- help for USGSImageryOnly_MapServer/GetTileImageInfo ---
```

```
GetTileImageInfo
```

```
Result = GetTileImageInfo(obj,MapName)
```

```
Inputs:
```

```
obj - USGSImageryOnly_MapServer object
```

```
MapName - string
```

```
Output:
```

```
Result - TileImageInfo object
```

See also `USGSImageryOnly_MapServer`.

This function returns a `TileImageInfo` object.

Read the documentation for the `TileImageInfo` object by clicking the link in the help display to `TileImageInfo`.

```
TileImageInfo(CacheTileFormat,CompressionQuality,Antialiasing) TileImageInfo object f
```

```

CacheTileFormat - string
    The cache tile format.
CompressionQuality - numeric scalar (XML int)
    The cache tile image compression quality.
Antialiasing - string
See also
USGSImageryOnly_MapServer.

```

MATLAB opens a document in the Help browser. The format information is `CacheTileFormat`.

Create the JPEG data. The following codes requires knowledge of the JPEG image format and the tiling scheme used by the USGS server.

```

% Get the default map name.
defaultMapName = GetDefaultMapName(wsd1);

% Get the map count.
count = GetMapCount(wsd1);

% Get the map name. There is only one map (count value),
% but the index is zero-based.
mapName = GetMapName(wsd1, count-1);

% Get information about the tiles.
tileImageInfo = GetTileImageInfo(wsd1, mapName);

% Get the format of the data.
format = tileImageInfo.CacheTileFormat;

% Since format is specified as 'Mixed' it implies that
% the result of GetMapTile is a JPEG-encoded stream.
% The map tiles are organized with the lowest level as
% the lowest level of detail and the tiles use
% zero-based indexing.
level = 0;
row = 0;
col = 0;
jpeg = GetMapTile(wsd1, mapName, level, row, col, format);

```

Write the JPEG-encoded data to a file. Use `imread` to read and decode the JPEG data and return a M-by-N-by-3 `uint8` matrix.

```

ext = '.jpg';
filename = ['USGSImageryOnly_MapServer' '0_0_0' ext];

```

```
fid = fopen(tilename, 'w');  
fwrite(fid, jpeg);  
fclose(fid);
```

View the map.

```
tileImage = imread(tilename);  
figure  
imshow(tileImage)
```

### Related Examples

- “Set Up WSDL Tools” on page 15-21



## Using WSDL Web Service with MATLAB

### In this section...

“What Are Web Services in MATLAB?” on page 15-27

“What are WSDL Documents?” on page 15-27

“What You Need to Use WSDL with MATLAB” on page 15-28

### What Are Web Services in MATLAB?


*Web services* allow applications running on disparate computers, operating systems, and development environments to communicate with each other. There are two ways to use Web services in MATLAB. When the service you want to use provides:

- RESTful (Representational state transfer), use the `webread` and `websave` functions in “Web Access”.
- Web Services Description Language (WSDL) document, use the MATLAB `matlab.wsd1.createWSDIClient` function, described in the following topics.

### What are WSDL Documents?

Using a Web service based on Web Services Description Language (WSDL) document technologies, client workstations access and execute APIs residing on a remote server. The client and server communicate via XML-formatted messages, following the W3C<sup>®</sup> SOAP protocol, and typically via the HTTP protocol.

Using the WSDL interface, MATLAB acts as a Web service client, providing functions you use to access existing services on a server. The functions facilitate communication with the server, relieving you of the need to work with XML, complex SOAP messages, and special Web service tools. Through these functions, you use services in your normal MATLAB environment, such as in the Command Window and in MATLAB programs you write.



### Diagram Showing Web Services in MATLAB

An organization that wants to make APIs available to disparate clients creates the APIs and related Web service facilities for the server. Organizations either choose to make the services available only to local clients via the organization's intranet, or offer them to the general public via the Web.

### What You Need to Use WSDL with MATLAB

You need to find out from your own organization and the organizations you work with if they provide a Web service of interest to you. There are publicly available services, some for free and some provided for a fee.

Functions for MATLAB WSDL Web services work with services that comply with the Basic Profile 1 to SOAP Binding specification.

You need to know basic information about the service you want to use, provided by the documentation for the service.

You need access to the server from the workstation where you use MATLAB. If there is a proxy server, provide any required settings using Web preferences. To do so, see “Specify Proxy Server Settings for Connecting to the Internet”.

## Access Services That Use WSDL Documents

A WSDL document uses a standard format to describe server operations, arguments, and transactions. The `matlab.wsd1.createWSDLCClient` function creates a MATLAB class that allows you to use the server APIs.

To use the `matlab.wsd1.createWSDLCClient` function, you need to know the location of the service WSDL document. The function works with WSDL documents that comply with the WS-I 1.0 standard and use one of these forms: RPC-literal, Document-literal, or Document-literal-wrapped. `matlab.wsd1.createWSDLCClient` does not support RPC-encoded.

You must download supported versions of the Oracle Java JDK and the Apache CXF programs.

To access a service:

- 1 Install and/or locate the Java JDK and Apache CXF programs.
- 2 Set the paths to the JDK and CXF programs using the `matlab.wsd1.setWSDLToolPath` function. Values for the paths are saved across sessions in your user preferences, so you only need to specify them once.
- 3 Change the MATLAB current folder to the location where you want to use the files generated from the WSDL document. You must have write-permission for this folder.
- 4 Run `matlab.wsd1.createWSDLCClient`, supplying the WSDL document location, which can be a URL or a path to a file.

The function converts the server APIs to a MATLAB class, and creates a class folder in the current folder. The class folder contains methods for using the server APIs. The function always creates a constructor method that has the same name as the class.

You only run the `matlab.wsd1.createWSDLCClient` function once. Then you can access the class anytime.

- 5 Create an object of the class whenever you want to use the operations of the service.
- 6 View information about the class to see what methods (operations) are available for you to use.
- 7 Use the methods of the object to run applications on and exchange data with the server.

MATLAB automatically converts XML data types to MATLAB types, and conversely.

### See Also

`matlab.wsd1.createWSDLClient` | `matlab.wsd1.setWSDLToolPath`

### Related Examples

- “Set Up WSDL Tools” on page 15-21

### More About

- “XML-MATLAB Data Type Conversion” on page 15-33
- “Limitations to WSDL Document Support” on page 15-35

## Error Handling

### In this section...

- “Considerations Using Web Services” on page 15-31
- “Error Handling with try/catch Statements” on page 15-31
- “Use a Local Copy of the WSDL Document” on page 15-31
- “Java Errors Accessing Service” on page 15-32
- “Anonymous Types Not Supported” on page 15-32

### Considerations Using Web Services

When creating MATLAB files that rely on a Web service, consider the following:

- A server issues a time-out error. Repeat the MATLAB command.
- Internet performance might make your application performance unpredictable.
- Conventions and established procedures for services and related technologies, like WSDL and SOAP, are still evolving. You might find inconsistencies or unexpected behavior when using a Web service.
- A service might change over time, which can impact its usage and results in MATLAB.
- A server issues other unrecoverable errors.

### Error Handling with try/catch Statements

Use the `error` function in try/catch statements to catch errors that result from method calls or from the `matlab.wsd1.createWSDLClient` function.

### Use a Local Copy of the WSDL Document

You can achieve better performance if you create a local copy and use the local copy instead of the version at the URL.

```
wsd1URL = ...  
['http://basemap.nationalmap.gov/arcgis/services/USGSImageryOnly/MapServer?wsdl'];  
wsdlFile = 'USGSImageryOnly_MapServer';  
if ~exist(wsd1File, 'file')
```

```
    websave(wsd1File, wsd1URL)
end
```

Use this strategy when you do not need immediate access to data at the URL.

## Java Errors Accessing Service

Once you access a service from MATLAB using the generated client code, you might get Java errors if:

- The WSDL for the service changes and you run `matlab1.wsd1.createWSDLClient` again for the same service in the same MATLAB session.
- You try to access the service using the regenerated code.

These errors are likely to occur if you modify the service between successive calls to `matlab1.wsd1.createWSDLClient`.

If you change a service you already accessed or generate the class files in another location, restart MATLAB.

## Anonymous Types Not Supported

Anonymous XML types are unnamed types embedded in other types.

For more information, see the IBM® article, “Web services hints and tips: avoid anonymous types,” at <http://www.ibm.com/developerworks/library/ws-avoid-anonymous-types>.

## See Also

error

## More About

- “Exception Handling in a MATLAB Application”

## External Websites

- W3C status codes for HTTP errors

## XML-MATLAB Data Type Conversion

MATLAB SOAP functions automatically convert XML data types used in SOAP messages to and from MATLAB types (classes). The following table contains the XML type and the corresponding MATLAB type for scalar values used in a WSDL document.

XML Schema Type	MATLAB Type Returned – Scalar
boolean	logical
byte	int8
unsignedByte	uint8
short	int16
unsignedShort	uint16
int	int32
unsignedInt	uint32
long	int64
unsignedLong	uint64
float	double
double	double
string	char vector
gYear, gMonth, gDay, gYearMonth, gMonthDay	calendarDuration array
dateTime	dateTime
date	dateTime with Year, Month, Day fields undefined.
time	dateTime with Hours, Minutes, Seconds fields undefined.
duration	duration if no year, month or day calendarDuration otherwise
NOTATION, QName	Character vector containing a legal QName
hexbinary, base64Binary	N-by-1 vector of uint8 representing byte values (0-255) of encoded data

XML Schema Type	MATLAB Type Returned—Scalar
decimal, integer, nonPositiveInteger, nonNegativeInteger, positiveInteger, negativeInteger	double array

The following table contains the XML type and the corresponding MATLAB type for arrays.

XML Schema Type—Array	MATLAB Type Returned—Array
array of string	N-by-1 cell array of characters
array of any <i>type</i>	N-by-1 vector of specified <i>type</i>
array of hexbinary, base64Binary	Not supported



## Limitations to WSDL Document Support

RPC-encoded WSDL documents are not supported. For these documents, use `createClassFromWsd1`.

The following WSDL documents are not supported:

- Documents that the Apache CXF program cannot compile into complete code.
- Documents that import other WSDL documents that contain WSDL type definitions.

### Workaround

Move all schema definitions from the imported files into the top-level WSDL file. Schema definitions appear as **schema** elements inside **types** elements.

If the imported files are not local, copy them locally and modify the `import` elements of all the files to point to the local files.

For example, consider the following top-level file.

```
<definitions>
  <import location="http://foo/bar?wsdl" />
  <types>
    ...top level type definitions...
  </types>
</definitions>
```

Download the file in the `location` attribute, `http://foo/bar?wsdl`, to a local file, and save it as `imported_file`. This file contains information similar to the following.

```
<wsdl:types>
  ...low level type definitions...
  <xsd:schema>
    ...schema definitions...
  </xsd:schema>
</wsdl:types>
```

Look for **types** and **schema** elements. The text prefixes, `wsdl` and `xsd`, do not have standard naming conventions and might not appear at all. Do not download `import` elements *within* the schema definitions. Move all **schema** elements in the imported file, including the opening and closing tags, from the imported file to the end of the

`types` element of the top-level file. Then delete the elements from the imported file. Do not modify existing `schema` elements in the top-level file. If the top-level file already contains a `types` section, add the `schema` elements to the existing `types` content. Otherwise, create a `types` section within the `definitions` element of the top-level file to contain the `schema` elements.

The top-level file now contains the following.

```
<definitions>
  <import location="imported_file" />
  <types>
    ...top level type definitions...
    <xsd:schema>
      ...schema definitions...
    </xsd:schema>
  </types>
</definitions>
```

The `imported_file` file contains the following.

```
<wsdl:types>
  ...low level type definitions...
</wsdl:types>
```

There must be exactly one `types` element in the top-level file inside the `definitions` element, containing all the schema defined in the imported WSDL files. None of the imported WSDL files should contain any `schema` elements.

- On Windows, documents that import other WSDL documents might fail if the imported URI contains certain punctuation characters.
- Some documents with messages containing multiple parts.
- Some documents with schemas containing anonymous complex types.
- Some documents defining an input parameter to an operation as a simple type. When you invoke such an operation, for example `GetMyOp`, MATLAB displays one of the following errors.

```
Error using xxx/GetMyOp. Too many input arguments.
```

Or:

```
Error using matlab.internal.callJava
No GetMyOp method with appropriate signature exists in Java class $Proxy57
```

# System Commands

---

- “Shell Escape Functions” on page 16-2
- “Run External Commands, Scripts, and Programs” on page 16-3
- “Change Environment Variable for Shell Command” on page 16-6

## Shell Escape Functions

It is sometimes useful to access your own C or Fortran programs using *shell escape functions*. Shell escape functions use the shell escape command `!` to make external stand-alone programs act like new MATLAB functions.

For example, the following function, `garfield.m`, uses an external function, `gareqn`, to find the solution to Garfield's equation.

```
function y = garfield(a,b,q,r)
save gardata a b q r
!gareqn
load gardata
```

This function:

- 1 Saves the input arguments `a`, `b`, `q`, and `r` to a MAT-file in the workspace using the `save` command.
- 2 Uses the shell escape operator to access a C or Fortran program called `gareqn` that uses the workspace variables to perform its computation. `gareqn` writes its results to the `gardata` MAT-file.
- 3 Loads the `gardata` MAT-file to obtain the results.

### Related Examples

- “Run External Commands, Scripts, and Programs” on page 16-3

## Run External Commands, Scripts, and Programs

The exclamation point character (!) sometimes called bang, is a *shell escape*. The character indicates that the rest of the input line is a command to the operating system. Use it to invoke utilities or call other executable programs without quitting MATLAB. To use the exclamation point in a factorial expression, call the `factorial` function.

For example, the following code opens the vi editor for a file named `yearlystats.m` on a UNIX platform.

```
!vi yearlystats.m
```

After the external program completes or you quit the program, the operating system returns control to MATLAB. Add `&` to the end of the line, such as

```
!dir &
```

on Windows platforms to display the output in a separate window or to run the application in background mode. For example:

```
!excel.exe &
```

opens Microsoft Excel software and returns control to the Command Window so you can continue running MATLAB language statements.

Restrictions maintained within the operating system determine the maximum length of the argument list you can provide as input to the bang (!) command.

For details about running external programs that return results and status, see the `unix`, `dos`, and `system` functions.

---

**Note** To execute operating system commands with specific environment variables, include all commands to the operating system within the `system` call. Separate the commands using `&` (ampersand) for DOS, and `;` (semicolon) for UNIX platforms. This applies to the MATLAB `!` (bang), `dos`, `unix`, and `system` functions. Another approach is to set environment variables before starting MATLAB.

---

On Mac platforms, you cannot run AppleScript (from Apple) directly from MATLAB. To run AppleScript commands, call the Apple Mac OS X `osascript` function using the MATLAB `unix` or `!` (bang) functions.

## Run UNIX Programs off System Path

You can run a UNIX program from MATLAB when the folder containing that file is not on the UNIX system path that is visible to MATLAB. To determine the system path that is visible to MATLAB, type the following in the Command Window:

```
getenv('PATH')
```

You can make modifications to the system path that persist for the current MATLAB session or across subsequent MATLAB sessions, as described in the sections that follow.

### Modify System Path for Current MATLAB Session

Do one of the following:

- Change the current folder in MATLAB to the folder that contains the program you want to run.
- Issue these commands using the Command Window:

```
path1 = getenv('PATH')
path1 = [path1 ' :/usr/local/bin']
setenv('PATH', path1)
!echo $PATH
```

If you restart MATLAB, the folder is no longer on the system path visible to MATLAB.

### Modify System Path Across MATLAB Sessions Within Current Shell Session

To add a folder to the system path from the shell:

- 1 Stop MATLAB.
- 2 Depending on the shell you are using, type one of the following at the system command prompt, where *myfolder* is the folder that contains the program you want to run:
  - If you are using `bash` or a related shell, type:

```
export PATH="$PATH:myfolder"
```
  - If you are using `tcsh` or a related shell, type:

```
setenv PATH "${PATH}:myfolder"
```
- 3 Start MATLAB.
- 4 In the MATLAB Command Window, type:

```
!echo $PATH
```

If you restart MATLAB within the current shell session, the folder remains on the system path visible to MATLAB. However, if you restart the shell session, and then restart MATLAB, the folder is no longer on the system path visible to MATLAB.

### **Modify System Path Across All MATLAB Sessions**

To modify the system path across shell and MATLAB sessions, add the following commands to the MATLAB startup file as described in “Startup Options in MATLAB Startup File”.

```
path1 = getenv('PATH')
path1 = [path1 ':/usr/local/bin']
setenv('PATH', path1)
!echo $PATH
```

### **See Also**

`dos` | `factorial` | `system` | `unix`

## Change Environment Variable for Shell Command

This example shows how to substitute a user-specified value for an environment variable value set by MATLAB when you call a function using the `system` command.

When you use the `system` command to call a function, the function inherits the MATLAB environment. To change environment variable values, use a shell wrapper. Use the environment variable `MATLAB_SHELL` to specify a shell containing your updated variable. This example uses a custom value for the environment variable `LD_LIBRARY_PATH`.

Create a wrapper file `matlab_shell.sh` in the folder `<PATH_TO_SHELL_SCRIPT>` with the following contents, where `<MY_LIBRARY_PATH>` is your custom value.

```
#!/bin/sh

LD_LIBRARY_PATH=<MY_LIBRARY_PATH>
export LD_LIBRARY_PATH

exec ${SHELL:-/bin/sh} $*
```

If you have a user-defined value for `SHELL`, the expression `${SHELL:-/bin/sh}` uses your `SHELL` value. Otherwise, MATLAB uses the Bourne shell.

From the operating system prompt, call MATLAB setting `MATLAB_SHELL` to:

```
<PATH_TO_SHELL_SCRIPT>/matlab_shell.sh
```

Display your value of `LD_LIBRARY_PATH` from the MATLAB command prompt.

```
!echo $LD_LIBRARY_PATH
```

Now when you call a function using the `system` command, the function uses the `LD_LIBRARY_PATH` value specified by `<MY_LIBRARY_PATH>`.

### See Also

`system`



# Serial Port I/O

---

- “Capabilities and Supported Interfaces and Platforms” on page 17-2
- “Overview of the Serial Port” on page 17-4
- “Getting Started with Serial I/O” on page 17-16
- “Create a Serial Port Object” on page 17-22
- “Connect to the Device” on page 17-26
- “Configure Communication Settings” on page 17-27
- “Write and Read Data” on page 17-28
- “Events and Callbacks” on page 17-46
- “Control Pins” on page 17-54
- “Debugging: Recording Information to Disk” on page 17-60
- “Save and Load” on page 17-66
- “Disconnect and Clean Up” on page 17-68
- “Property Reference” on page 17-70
- “Properties — Alphabetical List” on page 17-74

## Capabilities and Supported Interfaces and Platforms

### In this section...

“What Is the MATLAB Serial Port Interface?” on page 17-2

“Supported Serial Port Interface Standards” on page 17-3

“Supported Platforms” on page 17-3

“Using the Examples with Your Device” on page 17-3

### What Is the MATLAB Serial Port Interface?

The MATLAB serial port interface provides direct access to peripheral devices such as modems, printers, and scientific instruments that you connect to your computer's serial port. This interface is established through a serial port object. The serial port object supports functions and properties that allow you to

- Configure serial port communications
- Use serial port control pins
- Write and read data
- Use events and callbacks
- Record information to disk

Instrument Control Toolbox™ software provides additional serial port functionality. In addition to command-line access, this toolbox has a graphical tool called the Test & Measurement Tool, which allows you to communicate with, configure, and transfer data with your serial device without writing code. The Test & Measurement Tool generates MATLAB code for your serial device that you can later reuse to communicate with your device or to develop UI-based applications. The toolbox includes additional serial I/O utility functions that facilitate object creation and configuration, instrument communication, and so on. With the toolbox you can communicate with GPIB- or VISA-compatible instruments.

If you want to communicate with PC-compatible data acquisition hardware such as multifunction I/O boards, you need Data Acquisition Toolbox™ software.

For more information about these products, visit the MathWorks website at <http://www.mathworks.com/products>.

## Supported Serial Port Interface Standards

Over the years, several serial port interface standards have been developed. These standards include RS-232, RS-422, and RS-485 - all of which are supported by the MATLAB serial port object. Of these, the most widely used interface standard for connecting computers to peripheral devices is RS-232.

This guide assumes you are using the RS-232 standard, discussed in “Overview of the Serial Port” on page 17-4. Refer to your computer and device documentation to see which interface standard you can use.

## Supported Platforms

The MATLAB serial port interface is supported on:

- Linux 64-bit
- Mac OS X 64-bit
- Microsoft Windows 64-bit

## Using the Examples with Your Device

Many of the examples in this section reflect specific peripheral devices connected to a serial port — in particular a Tektronix® TDS 210 two-channel oscilloscope connected to the COM1 port, on a Windows platform. Therefore, many of the string commands are specific to this instrument and platform.

If you are using a different platform, or your peripheral device is connected to a different serial port, or if it accepts different commands, modify the examples accordingly.

## Overview of the Serial Port

In this section...
“Introduction” on page 17-4
“What Is Serial Communication?” on page 17-4
“The Serial Port Interface Standard” on page 17-4
“Connecting Two Devices with a Serial Cable” on page 17-5
“Serial Port Signals and Pin Assignments” on page 17-6
“Serial Data Format” on page 17-10
“Finding Serial Port Information for Your Platform” on page 17-13
“Using Virtual USB Serial Ports” on page 17-15
“Selected Bibliography” on page 17-15

### Introduction

For many serial port applications, you can communicate with your device without detailed knowledge of how the serial port works. If your application is straightforward, or if you are already familiar with the previously mentioned topics, you might want to begin with “The Serial Port Session” on page 17-16 to see how to use your serial port device with MATLAB software.

### What Is Serial Communication?

Serial communication is the most common low-level protocol for communicating between two or more devices. Normally, one device is a computer, while the other device can be a modem, a printer, another computer, or a scientific instrument such as an oscilloscope or a function generator.

As the name suggests, the serial port sends and receives bytes of information in a serial fashion — one bit at a time. These bytes are transmitted using either a binary (numerical) format or a text format.

### The Serial Port Interface Standard

The serial port interface for connecting two devices is specified by the TIA/EIA-232C standard published by the Telecommunications Industry Association.

The original serial port interface standard was given by RS-232, which stands for Recommended Standard number 232. The term *RS-232* is still in popular use, and is used in this guide when referring to a serial communication port that follows the TIA/EIA-232 standard. RS-232 defines these serial port characteristics:

- The maximum bit transfer rate and cable length
- The names, electrical characteristics, and functions of signals
- The mechanical connections and pin assignments

Primary communication is accomplished using three pins: the Transmit Data pin, the Receive Data pin, and the Ground pin. Other pins are available for data flow control, but are not required.

Other standards such as RS-485 define additional functionality such as higher bit transfer rates, longer cable lengths, and connections to as many as 256 devices.


## Connecting Two Devices with a Serial Cable

The RS-232 standard defines the two devices connected with a serial cable as the Data Terminal Equipment (DTE) and Data Circuit-Terminating Equipment (DCE). This terminology reflects the RS-232 origin as a standard for communication between a computer terminal and a modem.


Throughout this guide, your computer is considered a DTE, while peripheral devices such as modems and printers are considered DCEs. Many scientific instruments function as DTEs.

Because RS-232 mainly involves connecting a DTE to a DCE, the pin assignments are defined such that straight-through cabling is used, where pin 1 is connected to pin 1, pin 2 is connected to pin 2, and so on. The following diagram shows a DTE to DCE serial connection using the transmit data (TD) pin and the receive data (RD) pin.

For more information about serial port pins, see “Serial Port Signals and Pin Assignments” on page 17-6.



If you connect two DTEs or two DCEs using a straight serial cable, the TD pins on each device are connected to each other, and the RD pins on each device are connected to each other. Therefore, to connect two like devices, you must use a *null modem* cable. As shown in the following diagram, null modem cables cross the transmit and receive lines in the cable.




---


**Note:** You can connect multiple RS-422 or RS-485 devices to a serial port. If you have an RS-232/RS-485 adaptor, you can use the MATLAB serial port object with these devices.

---

## Serial Port Signals and Pin Assignments

Serial ports consist of two signal types: data signals and control signals. To support these signal types, as well as the signal ground, the RS-232 standard defines a 25-pin connection. However, most Windows and UNIX platforms use a 9-pin connection. In fact, only three pins are required for serial port communications: one for receiving data, one for transmitting data, and one for the signal ground.

The following diagram shows the pin assignment scheme for a 9-pin male connector on a DTE.



The pins and signals associated with the 9-pin connector are described in the following table. Refer to the RS-232 standard for a description of the signals and pin assignments used for a 25-pin connector.

### Serial Port Pin and Signal Assignments

Pin	Label	Signal Name	Signal Type
1	CD	Carrier Detect	Control
2	RD	Received Data	Data
3	TD	Transmitted Data	Data
4	DTR	Data Terminal Ready	Control
5	GND	Signal Ground	Ground
6	DSR	Data Set Ready	Control
7	RTS	Request to Send	Control
8	CTS	Clear to Send	Control
9	RI	Ring Indicator	Control

The term *data set* is synonymous with *modem* or *device*, while the term *data terminal* is synonymous with *computer*.

---

**Note:** The serial port pin and signal assignments are with respect to the DTE. For example, data is transmitted from the TD pin of the DTE to the RD pin of the DCE.

---


## Signal States

Signals can be in either an *active* state or an *inactive* state. An active state corresponds to the binary value 1, while an inactive state corresponds to the binary value 0. An active signal state is often described as *logic 1*, *on*, *true*, or a *mark*. An inactive signal state is often described as *logic 0*, *off*, *false*, or a *space*.

For data signals, the **on** state occurs when the received signal voltage is more negative than -3 volts, while the **off** state occurs for voltages more positive than 3 volts. For control signals, the **on** state occurs when the received signal voltage is more positive than 3 volts, while the **off** state occurs for voltages more negative than -3 volts. The voltage between -3 volts and +3 volts is considered a transition region, and the signal state is undefined.

To bring the signal to the **on** state, the controlling device *unasserts* (or *lowers*) the value for data pins and *asserts* (or *raises*) the value for control pins. Conversely, to bring the signal to the **off** state, the controlling device asserts the value for data pins and unasserts the value for control pins.

The following diagram shows the on and off states for a data signal and for a control signal.



### The Data Pins

Most serial port devices support *full-duplex* communication meaning that they can send and receive data at the same time. Therefore, separate pins are used for transmitting and receiving data. For these devices, the TD, RD, and GND pins are used. However, some types of serial port devices support only one-way or *half-duplex* communications. For these devices, only the TD and GND pins are used. This guide assumes that a full-duplex serial port is connected to your device.

The TD pin carries data transmitted by a DTE to a DCE. The RD pin carries data that is received by a DTE from a DCE.

### The Control Pins

The control pins of a 9-pin serial port are used to determine the presence of connected devices and control the flow of data. The control pins include

- “The RTS and CTS Pins” on page 17-8
- “The DTR and DSR Pins” on page 17-9
- “The CD and RI Pins” on page 17-9

### The RTS and CTS Pins

The RTS and CTS pins are used to signal whether the devices are ready to send or receive data. This type of data flow control—called *hardware handshaking*—is used



to prevent data loss during transmission. When enabled for both the DTE and DCE, hardware handshaking using RTS and CTS follows these steps:

- 1 The DTE asserts the RTS pin to instruct the DCE that it is ready to receive data.
- 2 The DCE asserts the CTS pin indicating that it is clear to send data over the TD pin. If data can no longer be sent, the CTS pin is unasserted.
- 3 The data is transmitted to the DTE over the TD pin. If data can no longer be accepted, the RTS pin is unasserted by the DTE and the data transmission is stopped.

To enable hardware handshaking in MATLAB software, see “Controlling the Flow of Data: Handshaking” on page 17-57.

#### **The DTR and DSR Pins**

Many devices use the DSR and DTR pins to signal if they are connected and powered. Signaling the presence of connected devices using DTR and DSR follows these steps:

- 1 The DTE asserts the DTR pin to request that the DCE connect to the communication line.
- 2 The DCE asserts the DSR pin to indicate it is connected.
- 3 DCE unasserts the DSR pin when it is disconnected from the communication line.

The DTR and DSR pins were originally designed to provide an alternative method of hardware handshaking. However, the RTS and CTS pins are usually used in this way, and not the DSR and DTR pins. Refer to your device documentation to determine its specific pin behavior.

#### **The CD and RI Pins**

The CD and RI pins are typically used to indicate the presence of certain signals during modem-modem connections.

A modem uses a CD pin to signal that it has made a connection with another modem, or has detected a carrier tone. CD is asserted when the DCE is receiving a signal of a suitable frequency. CD is unasserted if the DCE is not receiving a suitable signal.

The RI pin is used to indicate the presence of an audible ringing signal. RI is asserted when the DCE is receiving a ringing signal. RI is unasserted when the DCE is not receiving a ringing signal (e.g., it is between rings).

## Serial Data Format

The serial data format includes one start bit, between five and eight data bits, and one stop bit. A parity bit and an additional stop bit might be included in the format as well. The following diagram illustrates the serial data format.



The following notation expresses the format for serial port data:

number of data bits - parity type - number of stop bits

For example, 8-N-1 is interpreted as eight data bits, no parity bit, and one stop bit, while 7-E-2 is interpreted as seven data bits, even parity, and two stop bits.

The data bits are often referred to as a *character* because these bits usually represent an ASCII character. The remaining bits are called *framing bits* because they frame the data bits.

### Bytes Versus Values

A *byte* is the collection of bits that comprise the serial data format. At first, this term might seem inaccurate because a byte is 8 bits and the serial data format can range between 7 bits and 12 bits. However, when serial data is stored on your computer, the framing bits are stripped away, and only the data bits are retained. Moreover, eight data bits are always used regardless of the number of data bits specified for transmission, with the unused bits assigned a value of 0.

When reading or writing data, you might need to specify a *value*, which can consist of one or more bytes. For example, if you read one value from a device using the `int32` format, that value consists of four bytes. For more information about reading and writing values, see “Write and Read Data” on page 17-28.

### Synchronous and Asynchronous Communication

The RS-232 standard supports two types of communication protocols: synchronous and asynchronous.

Using the synchronous protocol, all transmitted bits are synchronized to a common clock signal. The two devices initially synchronize themselves to each other, and continually send characters to stay synchronized. Even when actual data is not really being sent, a constant flow of bits allows each device to know where the other is at any given time. That is, each bit that is sent is either actual data or an idle character. Synchronous communications allows faster data transfer rates than asynchronous methods, because additional bits to mark the beginning and end of each data byte are not required.

Using the asynchronous protocol, each device uses its own internal clock, resulting in bytes that are transferred at arbitrary times. So, instead of using time as a way to synchronize the bits, the data format is used.

In particular, the data transmission is synchronized using the start bit of the word, while one or more stop bits indicate the end of the word. The requirement to send these additional bits causes asynchronous communications to be slightly slower than synchronous. However, it has the advantage that the processor does not have to deal with the additional idle characters. Most serial ports operate asynchronously.

---

**Note:** When used in this guide, the terms *synchronous* and *asynchronous* refer to whether read or write operations block access to the MATLAB command line. For more information, see “Controlling Access to the MATLAB Command Line” on page 17-29.

---

### How Are the Bits Transmitted?

By definition, serial data is transmitted one bit at a time. The order in which the bits are transmitted is:

- 1 The start bit is transmitted with a value of 0.
- 2 The data bits are transmitted. The first data bit corresponds to the least significant bit (LSB), while the last data bit corresponds to the most significant bit (MSB).
- 3 The parity bit (if defined) is transmitted.
- 4 One or two stop bits are transmitted, each with a value of 1.

The *baud rate* is the number of bits transferred per second. The transferred bits include the start bit, the data bits, the parity bit (if defined), and the stop bits.

### Start and Stop Bits

As described in “Synchronous and Asynchronous Communication” on page 17-10, most serial ports operate asynchronously. This means that the transmitted byte must be

identified by start and stop bits. The start bit indicates when the data byte is about to begin; the stop bit(s) indicate(s) when the data byte has been transferred. The process of identifying bytes with the serial data format follows these steps:

- 1 When a serial port pin is idle (not transmitting data), it is in an **on** state.
- 2 When data is about to be transmitted, the serial port pin switches to an **off** state due to the start bit.
- 3 The serial port pin switches back to an **on** state due to the stop bit(s). This indicates the end of the byte.

### Data Bits

The data bits transferred through a serial port might represent device commands, sensor readings, error messages, and so on. The data can be transferred as either binary data or ASCII data.

Most serial ports use between five and eight data bits. Binary data is typically transmitted as eight bits. Text-based data is transmitted as either seven bits or eight bits. If the data is based on the ASCII character set, a minimum of seven bits is required because there are  $2^7$  or 128 distinct characters. If an eighth bit is used, it must have a value of 0. If the data is based on the extended ASCII character set, eight bits must be used because there are  $2^8$  or 256 distinct characters.

### The Parity Bit

The parity bit provides simple error (parity) checking for the transmitted data. The following table shows the types of parity checking.

#### Parity Types

Parity Type	Description
Even	The data bits plus the parity bit result in an even number of 1s.
Mark	The parity bit is always 1.
Odd	The data bits plus the parity bit result in an odd number of 1s.
Space	The parity bit is always 0.

Mark and space parity checking are seldom used because they offer minimal error detection. You might choose to not use parity checking at all.

The parity checking process follows these steps:

- 1 The transmitting device sets the parity bit to 0 or to 1, depending on the data bit values and the type of parity-checking selected.
- 2 The receiving device checks if the parity bit is consistent with the transmitted data. If it is, the data bits are accepted. If it is not, an error is returned.

---

**Note:** Parity checking can detect only 1-bit errors. Multiple-bit errors can appear as valid data.

---

For example, suppose the data bits 01110001 are transmitted to your computer. If even parity is selected, the parity bit is set to 0 by the transmitting device to produce an even number of 1s. If odd parity is selected, the parity bit is set to 1 by the transmitting device to produce an odd number of 1s.

## Finding Serial Port Information for Your Platform

This section describes the ways to find serial port information for Windows and UNIX platforms.

---


**Note:** Your operating system provides default values for all serial port settings. However, these settings are overridden by your MATLAB code, and will have no effect on your serial port application.

---

### Microsoft Windows Platform

- 1 Open the Windows Control Panel.
- 2 Click **Device Manager**.
- 3 In the **Device Manager** dialog box, expand the Ports node.
- 4 Double-click the **Communications Port (COM1)** node.
- 5 Select the **Port Settings** tab.

MATLAB displays the following Ports dialog box.



## UNIX Platform

To find serial port information for UNIX platforms, you need to know the serial port names. These names might vary between different operating systems.

On a Linux platform, serial port devices are typically named `ttyS0`, `ttyS1`, etc. Use the `setserial` command to display or configure serial port information. For example, to display which ports are available:

```
setserial -bg /dev/ttyS*
/dev/ttyS0 at 0x03f8 (irq = 4) is a 16550A
/dev/ttyS1 at 0x02f8 (irq = 3) is a 16550A
```

To display detailed information about `ttyS0`:

```
setserial -ag /dev/ttyS0
/dev/ttyS0, Line 0, UART: 16550A, Port: 0x03f8, IRQ: 4
      Baud_base: 115200, close_delay: 50, divisor: 0
```

```
closing_wait: 3000, closing_wait2: infinte  
Flags: spd_normal skip_test session_lockout
```

---

**Note:** If the `setserial -ag` command does not work, make sure you have read and write permission for the port.

---

For all supported UNIX platforms, use the `stty` command to display or configure serial port information. For example, to display serial port properties for `ttyS0`, enter:

```
stty -a < /dev/ttyS0
```

To configure the baud rate to 4800 bits per second, enter:

```
stty speed 4800 < /dev/ttyS0 > /dev/ttyS0
```

## Using Virtual USB Serial Ports

If you have devices that present themselves as serial ports on your operating system, you can use them as virtual USB serial ports in MATLAB. An example of such devices would be a USB Serial Dongle. For Bluetooth<sup>®</sup> devices, use the Bluetooth support in the Instrument Control Toolbox. See “Bluetooth Interface Overview” for more information.

MATLAB can communicate with these devices as long as the serial drivers provided by the device vendor are able to emulate the native hardware. Certain software, like HyperTerminal, does not require the device driver to fully implement and support the native hardware.

## Selected Bibliography

- [1] TIA/EIA-232-F, *Interface Between Data Terminal Equipment and Data Circuit-Terminating Equipment Employing Serial Binary Data Interchange*.
- [2] Jan Axelson, *Serial Port Complete*, Lakeview Research, Madison, WI, 1998.
- [3] *Instrument Communication Handbook*, IOTech, Inc., Cleveland, OH, 1991.
- [4] *TDS 200-Series Two Channel Digital Oscilloscope Programmer Manual*, Tektronix, Inc., Wilsonville, OR.
- [5] *Courier High Speed Modems User's Manual*, U.S. Robotics, Inc., Skokie, IL, 1994.

## Getting Started with Serial I/O

### In this section...

“Example: Getting Started” on page 17-16

“The Serial Port Session” on page 17-16

“Configuring and Returning Properties” on page 17-17

### Example: Getting Started

This example illustrates some basic serial port commands.

---

**Note:** This example is shown on a Windows platform.

---

If you have a device connected to the serial port COM1 and configured for a baud rate of 4800, execute the following example.

```
s = serial('COM1');
set(s, 'BaudRate', 4800);
fopen(s);
fprintf(s, '*IDN?')
out = fscanf(s);
fclose(s)
delete(s)
clear s
```

The `*IDN?` command queries the device for identification information, which is returned to `out`. If your device does not support this command, or if it is connected to a different serial port, modify the previous example accordingly.

---

**Note:** `*IDN?` is one of the commands supported by the Standard Commands for Programmable Instruments (SCPI) language, which is used by many modern devices. Refer to your device documentation to see if it supports the SCPI language.

---

### The Serial Port Session

This example describes the steps you use to perform any serial port task from beginning to end.



The serial port *session* comprises all the steps you are likely to take when communicating with a device connected to a serial port. These steps are:

- 1 Create a serial port object — Create a serial port object for a specific serial port using the `serial` creation function.

Configure properties during object creation if necessary. In particular, you might want to configure properties associated with serial port communications such as the baud rate, the number of data bits, and so on.

- 2 Connect to the device — Connect the serial port object to the device using the `fopen` function.

After the object is connected, alter the necessary device settings by configuring property values, read data, and write data.

- 3 Configure properties — To establish the desired serial port object behavior, assign values to properties using the `set` function or dot notation.

In practice, you can configure many of the properties at any time including during, or just after, object creation. Conversely, depending on your device settings and the requirements of your serial port application, you might be able to accept the default property values and skip this step.

- 4 Write and read data — Write data to the device using the `fprintf` or `fwrite` function, and read data from the device using the `fgetl`, `fgets`, `fread`, `fscanf`, or `readasynch` function.

The serial port object behaves according to the previously configured or default property values.

- 5 Disconnect and clean up — When you no longer need the serial port object, disconnect it from the device using the `fclose` function, remove it from memory using the `delete` function, and remove it from the MATLAB workspace using the `clear` command.

The serial port session is reinforced in many of the serial port documentation examples. To see a basic example that uses the steps shown above, see “Example: Getting Started” on page 17-16.

## Configuring and Returning Properties

This example describes how you display serial port property names and property values, and how you assign values to properties.

You establish the desired serial port object behavior by configuring property values. You can display or configure property values using the `set` function, the `get` function, or dot notation.

### Displaying Property Names and Property Values

After you create the serial port object, use the `set` function to display all the configurable properties to the command line. Additionally, if a property has a finite set of string values, `set` also displays these values.

```
s = serial('COM1');
set(s)
  ByteOrder: [ {littleEndian} | bigEndian ]
  BytesAvailableFcn
  BytesAvailableFcnCount
  BytesAvailableFcnMode: [ {terminator} | byte ]
  ErrorFcn
  InputBufferSize
  Name
  OutputBufferSize
  OutputEmptyFcn
  RecordDetail: [ {compact} | verbose ]
  RecordMode: [ {overwrite} | append | index ]
  RecordName
  Tag
  Timeout
  TimerFcn
  TimerPeriod
  UserData

SERIAL specific properties:
  BaudRate
  BreakInterruptFcn
  DataBits
  DataTerminalReady: [ {on} | off ]
  FlowControl: [ {none} | hardware | software ]
  Parity: [ {none} | odd | even | mark | space ]
  PinStatusFcn
  Port
  ReadAsyncMode: [ {continuous} | manual ]
  RequestToSend: [ {on} | off ]
  StopBits
  Terminator
```

Use the `get` function to display one or more properties and their current values to the command line. To display all properties and their current values:

```
get(s)
  ByteOrder = littleEndian
  BytesAvailable = 0
  BytesAvailableFcn =
  BytesAvailableFcnCount = 48
  BytesAvailableFcnMode = terminator
  BytesToOutput = 0
  ErrorFcn =
  InputBufferSize = 512
  Name = Serial-COM1
  OutputBufferSize = 512
  OutputEmptyFcn =
  RecordDetail = compact
  RecordMode = overwrite
  RecordName = record.txt
  RecordStatus = off
  Status = closed
  Tag =
  Timeout = 10
  TimerFcn =
  TimerPeriod = 1
  TransferStatus = idle
  Type = serial
  UserData = []
  ValuesReceived = 0
  ValuesSent = 0
```

SERIAL specific properties:

```
BaudRate = 9600
BreakInterruptFcn =
DataBits = 8
DataTerminalReady = on
FlowControl = none
Parity = none
PinStatus = [1x1 struct]
PinStatusFcn =
Port = COM1
ReadAsyncMode = continuous
RequestToSend = on
StopBits = 1
Terminator = LF
```

To display the current value for one property, supply the property name to `get`.

```
get(s, 'OutputBufferSize')
ans =
    512
```

To display the current values for multiple properties, include the property names as elements of a cell array.

```
get(s, {'Parity', 'TransferStatus'})
ans =
    'none'    'idle'
```

Use the dot notation to display a single property value.

```
s.Parity
ans =
    none
```

### **Configuring Property Values**

You can configure property values using the `set` function:

```
set(s, 'BaudRate', 4800);
```

or the dot notation:

```
s.BaudRate = 4800;
```

To configure values for multiple properties, supply multiple property name/property value pairs to `set`.

```
set(s, 'DataBits', 7, 'Name', 'Test1-serial')
```

Note that you can configure only one property value at a time using the dot notation.

In practice, you can configure many of the properties at any time while the serial port object exists — including during object creation. However, some properties are not configurable while the object is connected to the device or when recording information to disk. For information about when a property is configurable, see “Property Reference” on page 17-70.

### **Specifying Property Names**

Serial port property names are presented using mixed case. While this makes property names easier to read, use any case you want when specifying property names. For example, to configure the `BaudRate` property:

```
s.BaudRate = 4800;  
s.baudrate = 4800;
```

### Default Property Values

Whenever you do not explicitly define a value for a property, the default value is used. All configurable properties have default values.

---

**Note:** Your operating system provides default values for all serial port settings such as the baud rate. However, these settings are overridden by your MATLAB code and have no effect on your serial port application.

---

If a property has a finite set of string values, the default value is enclosed by {}. For example, the default value for the `Parity` property is `none`.

```
set(s,'Parity')  
[ {none} | odd | even | mark | space ]
```

You can find the default value for any property in the property reference pages.

## Create a Serial Port Object

### In this section...

“Overview of a Serial Port Object” on page 17-22

“Configuring Properties During Object Creation” on page 17-23

“The Serial Port Object Display” on page 17-24

“Creating an Array of Serial Port Objects” on page 17-24

### Overview of a Serial Port Object

The `serial` function requires the name of the serial port connected to your device as an input argument. Additionally, you can configure property values during object creation. To create a serial port object associated with the serial port enter:

```
s = serial('port');
```

This creates a serial port object associated with the serial port specified by `'port'`. If `'port'` does not exist, or if it is in use, you will not be able to connect the serial port object to the device. `'port'` object name will depend upon the platform that the serial port is on. The Instrument Control Toolbox function

```
instrhwinfo('serial')
```

provides a list of available serial ports. This list is an example of serial constructors on different platforms:

Platform	Serial Constructor
Linux 64-bit	<code>serial('/dev/ttyS0');</code>
Mac OS X 64-bit	<code>serial('/dev/tty.KeySerial1');</code>
Microsoft Windows 64-bit	<code>serial('com1');</code>

The serial port object `s` now exists in the MATLAB workspace. To display the class of `s`, use the `whos` command.

```
whos s
  Name      Size      Bytes  Class
```

```
s          1x1          512  serial object
Grand total is 11 elements using 512 bytes
```

---

**Note:** The first time you try to access a serial port in MATLAB using the `s = serial('port')` call, make sure that the port is free and is not already open in any other application. If the port is open in another application, MATLAB cannot access it. Once you have accessed in MATLAB, you can open the same port in other applications and MATLAB will continue to use it along with any other application that has it open as well.

---

Once the serial port object is created, the following properties are automatically assigned values. These general-purpose properties provide descriptive information about the serial port object based on the object type and the serial port.

### Descriptive General Purpose Properties

Property Name	Description
Name	Specify a descriptive name for the serial port object
Port	Indicate the platform-specific serial port name
Type	Indicate the object type

Display the values of these properties for `s` with the `get` function. On a Windows platform, it will look like this:

```
get(s,{'Name','Port','Type'})
ans =
    'Serial-COM1'    'COM1'    'serial'
```

### Configuring Properties During Object Creation

You can configure serial port properties during object creation. `serial` accepts property names and property values in the same format as the `set` function. For example, you can specify property name/property value pairs.

```
s = serial('port','BaudRate',4800,'Parity','even');
```

If you specify an invalid property name, the object is not created. However, if you specify an invalid value for some properties (for example, `BaudRate` is set to 50), the object

might be created but you are not informed of the invalid value until you connect the object to the device with the `fopen` function.

## The Serial Port Object Display

The serial port object provides you with a convenient display that summarizes important configuration and state information. You can invoke the display summary these three ways:

- Type the serial port object variable name at the command line.
- Exclude the semicolon when creating a serial port object.
- Exclude the semicolon when configuring properties using the dot notation.

To display summary information using the Workspace browser, right-click an instrument object and select **Display Summary** from the context menu.

The display summary for the serial port object `s` on a Windows platform is:

```
Serial Port Object : Serial-COM1
```

### Communication Settings

```
Port:          COM1
BaudRate:      9600
Terminator:    'LF'
```

### Communication State

```
Status:        closed
RecordStatus:  off
```

### Read/Write State

```
TransferStatus:  idle
BytesAvailable:  0
ValuesReceived:  0
ValuesSent:      0
```

## Creating an Array of Serial Port Objects

In MATLAB, you create an array from existing variables by concatenating those variables together. The same is true for serial port objects. For example, suppose you create the serial port objects `s1` and `s2` on a Windows platform.

```
s1 = serial('COM1');
```



```
s2 = serial('COM2');
```

Create a serial port object array, consisting of `s1` and `s2`, using the usual MATLAB syntax. To create the row array `x`, enter:

```
x = [s1 s2]
```

Instrument Object Array

Index:	Type:	Status:	Name:
1	serial	closed	Serial-COM1
2	serial	closed	Serial-COM2

To create the column array `y`, enter:

```
y = [s1;s2];
```

Note that you cannot create a matrix of serial port objects. For example, you cannot create the matrix:

```
z = [s1 s2;s1 s2];
??? Error using ==> serial/vertcat
Only a row or column vector of instrument objects can be created.
```

Depending on your application, you might want to pass an array of serial port objects to a function. For example, to configure the baud rate and parity for `s1` and `s2` using one call to `set`:

```
set(x, 'BaudRate', 19200, 'Parity', 'even')
```

## Connect to the Device

Before using the serial port object to write or read data, you must connect it to your device via the serial port specified in the `serial` function. You connect a serial port object to the device with the `fopen` function.

```
fopen(s)
```

Some properties are read only while the serial port object is connected and must be configured before using `fopen`. Examples include the `InputBufferSize` and the `OutputBufferSize` properties. To determine when you can configure a property, see “Property Reference” on page 17-70.

---


**Note:** You can create any number of serial port objects, but you can connect only one serial port object per MATLAB session to a given serial port at a time. However, the serial port is not locked by the session, so other applications or other instances of MATLAB software can access the same serial port, which could result in a conflict, with unpredictable results.

---

To verify that the serial port object is connected to the device, examine the `Status` property.

```
s.Status
ans =
open
```

As shown in the following illustration, the connection between the serial port object and the device is complete; data is readable and writable.



## Configure Communication Settings

Before you can write or read data, both the serial port object and the device must have identical communication settings. Configuring serial port communications involves specifying values for properties that control the baud rate and the serial data format. The following table describes these properties.

### Communication Properties

Property Name	Description
BaudRate	Specify the rate at which bits are transmitted
DataBits	Specify the number of data bits to transmit
Parity	Specify the type of parity checking
StopBits	Specify the number of bits used to indicate the end of a byte
Terminator	Specify the terminator character

---

**Note:** If the serial port object and the device communication settings are not identical, data is not readable or writable.

---

Refer to the device documentation for an explanation of its supported communication settings.

## Write and Read Data

### In this section...

“Before You Begin” on page 17-28

“Example — Introduction to Writing and Reading Data” on page 17-28

“Controlling Access to the MATLAB Command Line” on page 17-29

“Writing Data” on page 17-30

“Reading Data” on page 17-35

“Example — Writing and Reading Text Data” on page 17-41

“Example — Parsing Input Data Using textscan” on page 17-42

“Example — Reading Binary Data” on page 17-43

### Before You Begin

For many serial port applications, there are three important questions that you should consider when writing or reading data:

- Will the read or write function block access to the MATLAB command line?
- Is the data to be transferred binary (numerical) or text?
- Under what conditions will the read or write operation complete?

For write operations, these questions are answered in “Writing Data” on page 17-30. For read operations, these questions are answered in “Reading Data” on page 17-35.

### Example — Introduction to Writing and Reading Data

Suppose you want to return identification information for a Tektronix TDS 210 two-channel oscilloscope connected to the serial port COM1 on a Windows platform. This requires writing the \*IDN? command to the instrument using the `fprintf` function, and reading back the result of that command using the `fscanf` function.

```
s = serial('COM1');  
fopen(s)  
fprintf(s, '*IDN?')  
out = fscanf(s)
```

The resulting identification information is:

```
out =  
TEKTRONIX,TDS 210,0,CF:91.1CT FV:v1.16 TDS2CM:CMV:v1.04
```

End the serial port session.

```
fclose(s)  
delete(s)  
clear s
```

## Controlling Access to the MATLAB Command Line

You control access to the MATLAB command line by specifying whether a read or write operation is *synchronous* or *asynchronous*.

A synchronous operation blocks access to the command line until the read or write function completes execution. An asynchronous operation does not block access to the command line, and you can issue additional commands while the read or write function executes in the background.

The terms *synchronous* and *asynchronous* are often used to describe how the serial port operates at the hardware level. The RS-232 standard supports an asynchronous communication protocol. Using this protocol, each device uses its own internal clock. The data transmission is synchronized using the start bit of the bytes, while one or more stop bits indicate the end of the byte. For more information on start bits and stop bits, see “Serial Data Format” on page 17-10. The RS-232 standard also supports a synchronous mode where all transmitted bits are synchronized to a common clock signal.

At the hardware level, most serial ports operate asynchronously. However, using the default behavior for many of the read and write functions, you can mimic the operation of a synchronous serial port.

---


**Note:** When used in this guide, the terms *synchronous* and *asynchronous* refer to whether read or write operations block access to the MATLAB command-line. In other words, these terms describe how the software behaves, and not how the hardware behaves.

---

The two main advantages of writing or reading data asynchronously are:

- You can issue another command while the write or read function is executing.
- You can use all supported callback properties (see “Events and Callbacks” on page 17-46).

For example, because serial ports have separate read and write pins, you can simultaneously read and write data. This is illustrated in the following diagram.



## Writing Data

This section describes writing data to your serial port device in three parts:

- “The Output Buffer and Data Flow” on page 17-31 describes the flow of data from MATLAB software to the device.
- “Writing Text Data” on page 17-32 describes how to write text data (string commands) to the device.
- “Writing Binary Data” on page 17-34 describes how to write binary (numerical) data to the device.

The following table shows the functions associated with writing data.

### Functions Associated with Writing Data

Function Name	Description
<code>fprintf</code>	Write text to the device
<code>fwrite</code>	Write binary data to the device
<code>stopasync</code>	Stop asynchronous read and write operations

The following table shows the properties associated with writing data.

### Properties Associated with Writing Data

Property Name	Description
BytesToOutput	Number of bytes currently in the output buffer
OutputBufferSize	Size of the output buffer in bytes
Timeout	Waiting time to complete a read or write operation
TransferStatus	Indicate if an asynchronous read or write operation is in progress
ValuesSent	Total number of values written to the device

### The Output Buffer and Data Flow

The output buffer is computer memory allocated by the serial port object to store data that is to be written to the device. When writing data to your device, the data flow follows these two steps:


- 1 The data specified by the write function is sent to the output buffer.
- 2 The data in the output buffer is sent to the device.

The `OutputBufferSize` property specifies the maximum number of bytes that you can store in the output buffer. The `BytesToOutput` property indicates the number of bytes currently in the output buffer. The default values for these properties are:

```
s = serial('COM1');
get(s, {'OutputBufferSize', 'BytesToOutput'})
ans =
    [512]    [0]
```

If you attempt to write more data than can fit in the output buffer, an error is returned and no data is written.


For example, suppose you write the string command `*IDN?` to the TDS 210 oscilloscope using the `fprintf` function. As shown in the following diagram, the string is first written to the output buffer as six values.



- Bytes used during write
- Bytes unused during write

The `*IDN?` command consists of six values because the terminator is automatically written. Moreover, the default data format for the `fprintf` function specifies that one value corresponds to one byte. For more information about bytes and values, see “Bytes Versus Values” on page 17-10. `fprintf` and the terminator are discussed in “Writing Text Data” on page 17-32.

As shown in the following diagram, after the string is written to the output buffer, it is then written to the device via the serial port.



- Bytes used during write
- Bytes unused during write

**Writing Text Data**

You use the `fprintf` function to write text data to the device. For many devices, writing text data means writing string commands that change device settings, prepare the device to return data or status information, and so on.

For example, the `Display:Contrast` command changes the display contrast of the oscilloscope.



```
s = serial('COM1');
fopen(s)
fprintf(s, 'Display:Contrast 45')
```

By default, `fprintf` writes data using the `%s\n` format because many serial port devices accept only text-based commands. However, you can specify many other formats, as described in the `fprintf` reference pages.

To verify the number of values sent to the device, use the `ValuesSent` property.

```
s.ValuesSent
ans =
    20
```

Note that the `ValuesSent` property value includes the terminator because each occurrence of `\n` in the command sent to the device is replaced with the `Terminator` property value.

```
s.Terminator
ans =
LF
```

The default value of `Terminator` is the linefeed character. The terminator required by your device will be described in its documentation.

### Synchronous Versus Asynchronous Write Operations

By default, `fprintf` operates synchronously and blocks the MATLAB command line until execution completes. To write text data asynchronously to the device, you must specify `async` as the last input argument to `fprintf`.

```
fprintf(s, 'Display:Contrast 45', 'async')
```

Asynchronous operations do not block access to the MATLAB command line. Additionally, while an asynchronous write operation is in progress, you can:

- Execute an asynchronous read operation because serial ports have separate pins for reading and writing
- Make use of all supported callback properties

To determine which asynchronous operations are in progress, use the `TransferStatus` property. If no asynchronous operations are in progress, `TransferStatus` is `idle`.

```
s.TransferStatus
```

```
ans =  
idle
```

### Completing a Write Operation with `fprintf`

A synchronous or asynchronous write operation using `fprintf` completes when:

- The specified data is written.
- The time specified by the `Timeout` property passes.

Stop an asynchronous write operation with the `stopasync` function.

### Rules for Writing the Terminator

The `Terminator` property value replaces all occurrences of `\n` in `cmd`. Therefore, when you use the default format `%s\n`, all commands written to the device end with this property value. Refer to your device documentation for the terminator required by your device.

### Writing Binary Data

You use the `fwrite` function to write binary data to the device. Writing binary data means writing numerical values. A typical application for writing binary data involves writing calibration data to an instrument such as an arbitrary waveform generator.

---

**Note:** Some serial port devices accept only text-based commands. These commands might use the SCPI language or some other vendor-specific language. Therefore, you might need to use the `fprintf` function for all write operations.

---

By default, `fwrite` translates values using the `uchar` precision. However, you can specify many other precisions as described in the reference pages for this function.

By default, `fwrite` operates synchronously. To write binary data asynchronously to the device, you must specify `async` as the last input argument to `fwrite`. For more information about synchronous and asynchronous write operations, see “Writing Text Data” on page 17-32. For a description of the rules used by `fwrite` to complete a write operation, refer to its reference pages.

### Troubleshooting Common Errors

Use this table to identify common `fprintf` errors.

Error	Occurs when	Troubleshooting
<p>??? Error using ==&gt; serial.fwrite at 199 OBJ must be connected to the hardware with FOPEN.</p>	<p>You perform a write operation and the serial port object is not connected to the device.</p>	<p>Use <code>fopen</code> to establish a connection to the device.</p>
<p>??? Error using ==&gt; serial.fwrite at 199 The number of bytes written must be less than or equal to <code>OutputBufferSize-BytesToOutput</code>.</p>	<p>The output buffer is not able to hold all the data to be written.</p>	<p>Specify the size of the output buffer with the <code>OutputBufferSize</code> property.</p>
<p>??? Error using ==&gt; serial.fwrite at 192 FWRITE cannot be called. The <code>FlowControl</code> property is set to 'hardware' and the Clear To Send (CTS) pin is high. This could indicate that the serial device may not be turned on, may not be connected, or does not use hardware handshaking</p>	<ul style="list-style-type: none"> <li>• You set the <code>flowcontrol</code> property on a serial object to <code>hardware</code>.</li> <li>• The device is either not connected or a connected device is not asserting that is ready to receive data.</li> </ul>	<p>Check your remote device status and flow control settings to see if hardware flow control is causing MATLAB errors.</p>

## Reading Data

This section describes reading data from your serial port device in three parts:

- “The Input Buffer and Data Flow” on page 17-36 describes the flow of data from the device to MATLAB software.
- “Reading Text Data” on page 17-38 describes how to read from the device, and format the data as text.

- “Reading Binary Data” on page 17-40 describes how to read binary (numerical) data from the device.

The following table shows the functions associated with reading data.

#### Functions Associated with Reading Data

Function Name	Description
<code>fgetl</code>	Read one line of text from the device and discard the terminator
<code>fgets</code>	Read one line of text from the device and include the terminator
<code>fread</code>	Read binary data from the device
<code>fscanf</code>	Read data from the device and format as text
<code>readasync</code>	Read data asynchronously from the device
<code>stopasync</code>	Stop asynchronous read and write operations

The following table shows the properties associated with reading data.

#### Properties Associated with Reading Data

Property Name	Description
<code>BytesAvailable</code>	Number of bytes available in the input buffer
<code>InputBufferSize</code>	Size of the input buffer in bytes
<code>ReadAsyncMode</code>	Specify whether an asynchronous read operation is continuous or manual
<code>Timeout</code>	Waiting time to complete a read or write operation
<code>TransferStatus</code>	Indicate if an asynchronous read or write operation is in progress
<code>ValuesReceived</code>	Total number of values read from the device

#### The Input Buffer and Data Flow

The input buffer is computer memory allocated by the serial port object to store data that is to be read from the device. When reading data from your device, the data flow follows these two steps:


- 1 The data read from the device is stored in the input buffer.
- 2 The data in the input buffer is returned to the MATLAB variable specified by the read function.

The `InputBufferSize` property specifies the maximum number of bytes you can store in the input buffer. The `BytesAvailable` property indicates the number of bytes currently available to be read from the input buffer. The default values for these properties are:

```
s = serial('COM1');
get(s,{'InputBufferSize','BytesAvailable'})
ans =
    [512]    [0]
```


If you attempt to read more data than can fit in the input buffer, an error is returned and no data is read.

For example, suppose you use the `fscanf` function to read the text-based response of the `*IDN?` command previously written to the TDS 210 oscilloscope. As shown in the following diagram, the text data is first read into the input buffer via the serial port.



Note that for a given read operation, you might not know the number of bytes returned by the device. Therefore, you might need to preset the `InputBufferSize` property to a sufficiently large value before connecting the serial port object.

As shown in the following diagram, after the data is stored in the input buffer, it is then transferred to the output variable specified by `fscanf`.



- Bytes used during read
- Bytes unused during read

### Reading Text Data

You use the `fgetl`, `fgets`, and `fscanf` functions to read data from the device, and format the data as text.

For example, suppose you want to return identification information for the oscilloscope. This requires writing the `*IDN?` command to the instrument, and then reading back the result of that command.

```
s = serial('COM1');
fopen(s)
fprintf(s, '*IDN?')
out = fscanf(s)
out =
TEKTRONIX,TDS 210,0,CF:91.1CT FV:v1.16 TDS2CM:CMV:v1.04
```

By default, `fscanf` reads data using the `%c` format because the data returned by many serial port devices is text based. However, you can specify many other formats as described in the `fscanf` reference pages.

To verify the number of values read from the device—including the terminator, use the `ValuesReceived` property.

```
s.ValuesReceived
ans =
    56
```

### Synchronous Versus Asynchronous Read Operations

You specify whether read operations are synchronous or asynchronous with the `ReadAsyncMode` property. You can configure `ReadAsyncMode` to `continuous` or `manual`.

If `ReadAsyncMode` is `continuous` (the default value), the serial port object continuously queries the device to determine if data is available to be read. If data is available, it is asynchronously stored in the input buffer. To transfer the data from the input buffer to MATLAB, use one of the synchronous (blocking) read functions such as `fgetl` or `fscanf`. If data is available in the input buffer, these functions return quickly.

```
s.ReadAsyncMode = 'continuous';
fprintf(s, '*IDN?')
s.BytesAvailable
ans =
    56
out = fscanf(s);
```

If `ReadAsyncMode` is `manual`, the serial port object does not continuously query the device to determine if data is available to be read. To read data asynchronously, use the `readasync` function. Then use one of the synchronous read functions to transfer data from the input buffer to MATLAB.

```
s.ReadAsyncMode = 'manual';
fprintf(s, '*IDN?')
s.BytesAvailable
ans =
    0
readasync(s)
s.BytesAvailable
ans =
    56
out = fscanf(s);
```

Asynchronous operations do not block access to the MATLAB command line. Additionally, while an asynchronous read operation is in progress, you can:

- Execute an asynchronous write operation because serial ports have separate pins for reading and writing
- Make use of all supported callback properties

To determine which asynchronous operations are in progress, use the `TransferStatus` property. If no asynchronous operations are in progress, then `TransferStatus` is `idle`.

```
s.TransferStatus
ans =
idle
```

### Rules for Completing a Read Operation with `fscanf`

A read operation with `fscanf` blocks access to the MATLAB command line until:

- The terminator specified by the `Terminator` property is read.
- The time specified by the `Timeout` property passes.
- The specified number of values specified is read.
- The input buffer is filled.

### Reading Binary Data

You use the `fread` function to read binary data from the device. Reading binary data means that you return numerical values to MATLAB.

For example, suppose you want to return the cursor and display settings for the oscilloscope. This requires writing the `CURSOR?` and `DISPLAY?` commands to the instrument, and then reading back the results of those commands.

```
s = serial('COM1');  
fopen(s)  
fprintf(s, 'CURSOR?')  
fprintf(s, 'DISPLAY?')
```

Because the default value for the `ReadAsyncMode` property is `continuous`, data is asynchronously returned to the input buffer as soon as it is available from the device. To verify the number of values read, use the `BytesAvailable` property.

```
s.BytesAvailable  
ans =  
    69
```

To return the data to MATLAB, use any of the synchronous read functions. However, if you use `fgetl`, `fgets`, or `fscanf`, you must issue the function twice because there are two terminators stored in the input buffer. To return all the data to MATLAB in one function call, use `fread`.

```
out = fread(s,69);
```

By default, `fread` returns numerical values in double precision arrays. However, you can specify many other precisions as described in the `fread` reference pages. To convert the numerical data to text, use the MATLAB `char` function.



```

val = char(out) '
val =
HBARS;CH1;SECONDS;-1.0E-3;1.0E-3;VOLTS;-6.56E-1;6.24E-1
YT;DOTS;0;45

```

For more information about synchronous and asynchronous read operations, see “Reading Text Data” on page 17-38. For a description of the rules used by `fread` to complete a read operation, refer to its reference pages.

## Example — Writing and Reading Text Data

This example illustrates how to communicate with a serial port instrument by writing and reading text data.

The instrument is a Tektronix TDS 210 two-channel oscilloscope connected to the COM1 port. Therefore, many of the following commands are specific to this instrument. A sine wave is input into channel 2 of the oscilloscope, and your job is to measure the peak-to-peak voltage of the input signal.

- 1 Create a serial port object — Create the serial port object `s` associated with serial port COM1.

```
s = serial('COM1');
```

- 2 Connect to the device — Connect `s` to the oscilloscope. Because the default value for the `ReadAsyncMode` property is `continuous`, data is asynchronously returned to the input buffer as soon as it is available from the instrument.

```
fopen(s)
```

- 3 Write and read data — Write the `*IDN?` command to the instrument using `fprintf`, and then read back the result of the command using `fscanf`.

```

fprintf(s,'*IDN?')
idn = fscanf(s)
idn =
TEKTRONIX,TDS 210,0,CF:91.1CT FV:v1.16 TDS2CM:CMV:v1.04

```

You need to determine the measurement source. Possible measurement sources include channel 1 and channel 2 of the oscilloscope.

```

fprintf(s,'MEASUREMENT:IMMED:SOURCE?')
source = fscanf(s)
source =

```

CH1

The scope is configured to return a measurement from channel 1. Because the input signal is connected to channel 2, you must configure the instrument to return a measurement from this channel.

```
fprintf(s,'MEASUREMENT:IMMED:SOURCE CH2')
fprintf(s,'MEASUREMENT:IMMED:SOURCE?')
source = fscanf(s)
source =
CH2
```

Configure the scope to return the peak-to-peak voltage, and then request the value of this measurement.

```
fprintf(s,'MEASUREMENT:MEAS1:TYPE PK2PK')
fprintf(s,'MEASUREMENT:MEAS1:VALUE?')
```

Transfer data from the input buffer to MATLAB using `fscanf`.

```
ptop = fscanf(s,'%g')
ptop =
2.0199999809E0
```

- 4 Disconnect and clean up — When you no longer need `s` disconnect it from the instrument and remove it from memory and from the MATLAB workspace.

```
fclose(s)
delete(s)
clear s
```

## Example — Parsing Input Data Using `textscan`

This example illustrates how to use the `textscan` function to parse and format data that you read from a device. `textscan` is particularly useful when you want to parse a string into one or more variables, where each variable has its own specified format.

The instrument is a Tektronix TDS 210 two-channel oscilloscope connected to the serial port COM1.

- 1 Create a serial port object — Create the serial port object `s` associated with serial port COM1.

```
s = serial('COM1');
```

- 2 Connect to the device — Connect `s` to the oscilloscope. Because the default value for the `ReadAsyncMode` property is `continuous`, data is asynchronously returned to the input buffer as soon as it is available from the instrument.

```
fopen(s)
```

- 3 Write and read data — Write the `RS232?` command to the instrument using `fprintf`, and then read back the result of the command using `fscanf`. `RS232?` queries the RS-232 settings and returns the baud rate, the software flow control setting, the hardware flow control setting, the parity type, and the terminator.

```
fprintf(s, 'RS232?')
data = fscanf(s)
data =
9600;0;0;NONE;LF
```

Use the `textscan` function to parse and format the `data` variable into five new variables.

```
C = textscan(a, '%d%d%d%s', 'delimiter', '');
[br, sfc, hfc, par, tm] = deal(C{:});
br =
    9600
sfc =
     0
hfc =
     0
par =
    'NONE'
tm =
    'LF'
```

- 4 Disconnect and clean up — When you no longer need `s`, you should disconnect it from the instrument, and remove it from memory and from the MATLAB workspace.

```
fclose(s)
delete(s)
clear s
```

## Example — Reading Binary Data

This example shows how you to download the TDS 210 oscilloscope screen display to MATLAB. The screen display data is transferred and saved to disk using the Windows bitmap format. This data provides a permanent record of your work, and is an easy way to document important signal and scope parameters.

Because the amount of data transferred is expected to be fairly large, it is asynchronously returned to the input buffer as soon as it is available from the instrument. This allows you to perform other tasks as the transfer progresses. Additionally, the scope is configured to its highest baud rate of 19,200.

- 1 Create a serial port object — Create the serial port object `s` associated with serial port COM1.

```
s = serial('COM1');
```

- 2 Configure property values — Configure the input buffer to accept a reasonably large number of bytes, and configure the baud rate to the highest value supported by the scope.

```
s.InputBufferSize = 50000;  
s.BaudRate = 19200;
```

- 3 Connect to the device — Connect `s` to the oscilloscope. Because the default value for the `ReadAsyncMode` property is `continuous`, data is asynchronously returned to the input buffer as soon as it is available from the instrument.

```
fopen(s)
```

- 4 Write and read data — Configure the scope to transfer the screen display as a bitmap.

```
fprintf(s, 'HARDCOPY:PORT RS232')  
fprintf(s, 'HARDCOPY:FORMAT BMP')  
fprintf(s, 'HARDCOPY START')
```

Wait until all the data is sent to the input buffer, and then transfer the data to the MATLAB workspace as unsigned 8-bit integers.

```
out = fread(s,s.BytesAvailable, 'uint8');
```

- 5 Disconnect and clean up — When you no longer need `s`, disconnect it from the instrument and remove it from memory and from the MATLAB workspace.

```
fclose(s)  
delete(s)  
clear s
```

### Viewing the Bitmap Data

To view the bitmap data, follow these steps:

- 1 Open a disk file.

- 2 Write the data to the disk file.
- 3 Close the disk file.
- 4 Read the data into MATLAB using the `imread` function.
- 5 Scale and display the data using the `imagesc` function.


Note that the file I/O versions of the `fopen`, `fwrite`, and `fclose` functions are used.

```
fid = fopen('test1.bmp','w');
fwrite(fid,out,'uint8');
fclose(fid)
a = imread('test1.bmp','bmp');
imagesc(a)
```

Because the scope returns the screen display data using only two colors, an appropriate colormap is selected.

```
mymap = [0 0 0; 1 1 1];
colormap(mymap)
```

The following diagram shows the resulting bitmap image.



## Events and Callbacks

### In this section...

“Introduction” on page 17-46

“Example — Introduction to Events and Callbacks” on page 17-46

“Event Types and Callback Properties” on page 17-47

“Respond To Event Information” on page 17-49

“Create and Execute Callback Functions” on page 17-51

“Enable Callback Functions After They Error” on page 17-52

“Example — Using Events and Callbacks” on page 17-52

### Introduction

You can enhance the power and flexibility of your serial port application by using *events*. An event occurs after a condition is met and might result in one or more callbacks.

While the serial port object is connected to the device, use events to display a message, display data, analyze data, and so on. Callbacks are controlled through *callback properties* and *callback functions*. All event types have an associated callback property. Callback functions are MATLAB functions that you construct to suit your specific application needs.

You execute a callback when a particular event occurs by specifying the name of the callback function as the value for the associated callback property.

### Example — Introduction to Events and Callbacks

This example uses the callback function `instrcallback` to display a message to the command line when a bytes-available event occurs. The event is generated when the terminator is read.

```
s = serial('COM1');
s.BytesAvailableFcnMode = 'terminator';
s.BytesAvailableFcn = @instrcallback;
fopen(s)
fprintf(s, '*IDN?')
out = fscanf(s);
```

MATLAB displays:

```
BytesAvailable event occurred at 17:01:29 for the object:
Serial-COM1.
```

End the serial port session.

```
fclose(s)
delete(s)
clear s
```

To see the code for the built-in `instrcallback` function, use the `type` command.

## Event Types and Callback Properties

The following table describes serial port event types and callback properties. This table has two columns and nine rows. In the first column (event type), the second item (bytes available) applies to rows 2 through 4. Also, in the first column the last item (timer) applies to rows 8 and 9.

### Event Types and Callback Properties

Event Type	Associated Properties
Break interrupt	BreakInterruptFcn
Bytes available	BytesAvailableFcn
	BytesAvailableFcnCount
	BytesAvailableFcnMode
Error	ErrorFcn
Output empty	OutputEmptyFcn
Pin status	PinStatusFcn
Timer	TimerFcn
	TimerPeriod

### Break-Interrupt Event

A break-interrupt event is generated immediately after a break interrupt is generated by the serial port. The serial port generates a break interrupt when the received data has been in an inactive state longer than the transmission time for one character.

This event executes the callback function specified for the `BreakInterruptFcn` property. It can be generated for both synchronous and asynchronous read and write operations.

### **Bytes-Available Event**

A bytes-available event is generated immediately after a predetermined number of bytes are available in the input buffer or a terminator is read, as determined by the `BytesAvailableFcnMode` property.

If `BytesAvailableFcnMode` is `byte`, the bytes-available event executes the callback function specified for the `BytesAvailableFcn` property every time the number of bytes specified by `BytesAvailableFcnCount` is stored in the input buffer. If `BytesAvailableFcnMode` is `terminator`, the callback function executes every time the character specified by the `Terminator` property is read.

This event can be generated only during an asynchronous read operation.

### **Error Event**

An error event is generated immediately after an error occurs.

This event executes the callback function specified for the `ErrorFcn` property. It can be generated only during an asynchronous read or write operation.

An error event is generated when a time-out occurs. A time-out occurs if a read or write operation does not successfully complete within the time specified by the `Timeout` property. An error event is not generated for configuration errors such as setting an invalid property value.

### **Output-Empty Event**

An output-empty event is generated immediately after the output buffer is empty.

This event executes the callback function specified for the `OutputEmptyFcn` property. It can be generated only during an asynchronous write operation.

### **Pin Status Event**

A pin status event is generated immediately after the state (pin value) changes for the CD, CTS, DSR, or RI pins. For a description of these pins, see “Serial Port Signals and Pin Assignments” on page 17-6.



This event executes the callback function specified for the `PinStatusFcn` property. It can be generated for both synchronous and asynchronous read and write operations.

### Timer Event

A timer event is generated when the time specified by the `TimerPeriod` property passes. Time is measured relative to when the serial port object is connected to the device.

This event executes the callback function specified for the `TimerFcn` property. Note that some timer events might not be processed if your system is significantly slowed or if the `TimerPeriod` value is too small.

## Respond To Event Information

You can respond to event information in a callback function or in a record file. Event information is stored in a callback function using two fields: `Type` and `Data`. The `Type` field contains the event type, while the `Data` field contains event-specific information. As described in “Create and Execute Callback Functions” on page 17-51, these two fields are associated with a structure that you define in the callback function header. To learn about recording data and event information to a record file, see “Debugging: Recording Information to Disk” on page 17-60.

The following table shows event types and the values for the `Type` and `Data` fields. The table has three columns and 15 rows. Items in the first column (event type) span several rows, as follows:

Break interrupt: rows 1 and 2

Bytes available: rows 3 and 4

Error: rows 5 through 7

Output empty: rows 8 and 9

Pin status: rows 10 through 13

Timer: rows 14 and 15

### Event Information

Event Type	Field	Field Value
Break interrupt	Type	BreakInterrupt
	Data	

Event Type	Field	Field Value
	Data.AbsTime	day-month-year hour:minute:second
Bytes available	Type	BytesAvailable
	Data.AbsTime	day-month-year hour:minute:second
Error	Type	Error
	Data.AbsTime	day-month-year hour:minute:second
	Data.Message	An error string
Output empty	Type	OutputEmpty
	Data.AbsTime	day-month-year hour:minute:second
Pin status	Type	PinStatus
	Data.AbsTime	day-month-year hour:minute:second
	Data.Pin	CarrierDetect, ClearToSend, DataSetReady, or RingIndicator
	Data.PinValue	on or off
Timer	Type	Timer
	Data.AbsTime	day-month-year hour:minute:second

The following topics describe the Data field values.

### AbsTime Field

The AbsTime field, defined for all events, is the absolute time the event occurred. The absolute time is returned using the `CLOCK` format: day-month-year hour:minute:second.

### Pin Field

The pin status event uses the Pin field to indicate if the CD, CTS, DSR, or RI pins changed state. For a description of these pins, see “Serial Port Signals and Pin Assignments” on page 17-6.

### PinValue Field

The pin status event uses the `PinValue` field to indicate the state of the CD, CTS, DSR, or RI pins. Possible values are `on` or `off`.

### Message Field

The error event uses the `Message` field to store the descriptive message that is generated when an error occurs.

## Create and Execute Callback Functions

To specify the callback function to be executed when a specific event type occurs, include the name of the file as the value for the associated callback property. You can specify the callback function as a function handle or as a string cell array element. For information about function handles, see “Create Function Handle”.

For example, to execute the callback function `mycallback` every time the terminator is read from your device:

```
s.BytesAvailableFcnMode = 'terminator';  
s.BytesAvailableFcn = @mycallback;
```

Alternatively, you can specify the callback function as a cell array.

```
s.BytesAvailableFcn = {'mycallback'};
```

Callback functions require at least two input arguments. The first argument is the serial port object. The second argument is a variable that captures the event information shown in the table, Event Information. This event information pertains only to the event that caused the callback function to execute. The function header for `mycallback` is:

```
function mycallback(obj,event)
```

You pass additional parameters to the callback function by including both the callback function and the parameters as elements of a cell array. For example, to pass the MATLAB variable `time` to `mycallback`:

```
time = datestr(now,0);  
s.BytesAvailableFcnMode = 'terminator';  
s.BytesAvailableFcn = {@mycallback,time};
```

Alternatively, you can specify the callback function as a string in the cell array.

```
s.BytesAvailableFcn = {'mycallback',time};
```

The corresponding function header is:

```
function mycallback(obj,event,time)
```

If you pass additional parameters to the callback function, they must be included in the function header after the two required arguments.

---

**Note:** You can also specify the callback function as a string. In this case, the callback is evaluated in the MATLAB workspace and no requirements are made on the input arguments of the callback function.

---

## Enable Callback Functions After They Error

If an error occurs while a callback function is executing the following occurs:

- The callback function is automatically disabled.
- A warning is displayed at the command line, indicating that the callback function is disabled.

If you want to enable the same callback function, set the callback property to the same value or disconnect the object with the `fclose` function. If you want to use a different callback function, the callback is enabled when you configure the callback property to the new value.

## Example — Using Events and Callbacks

This example uses the callback function `instrcallback` to display event-related information to the command line when a bytes-available event or an output-empty event occurs.

- 1 Create a serial port object — Create the serial port object `s` associated with serial port COM1.

```
s = serial('COM1');
```

- 2 Configure properties — Configure `s` to execute the callback function `instrcallback` when a bytes-available event or an output-empty event occurs. Because `instrcallback` requires the serial port object and event information to be passed as input arguments, the callback function is specified as a function handle.

```
s.BytesAvailableFcnMode = 'terminator';
s.BytesAvailableFcn = @instrcallback;
s.OutputEmptyFcn = @instrcallback;
```

- 3 Connect to the device — Connect `s` to the Tektronix TDS 210 oscilloscope. Because the default value for the `ReadAsyncMode` property is `continuous`, data is asynchronously returned to the input buffer as soon as it is available from the instrument.

```
fopen(s)
```

- 4 Write and read data — Write the `RS232?` command asynchronously to the oscilloscope. This command queries the RS-232 settings and returns the baud rate, the software flow control setting, the hardware flow control setting, the parity type, and the terminator.

```
fprintf(s, 'RS232?', 'async')
```

`instrcallback` is called after the `RS232?` command is sent, and when the terminator is read. The resulting displays are:

```
OutputEmpty event occurred at 17:37:21 for the object:
Serial-COM1.
```

```
BytesAvailable event occurred at 17:37:21 for the object:
Serial-COM1.
```

Read the data from the input buffer.

```
out = fscanf(s)
out =
9600;0;0;NONE;LF
```

- 5 Disconnect and clean up — When you no longer need `s`, disconnect it from the instrument and remove it from memory and from the MATLAB workspace.

```
fclose(s)
delete(s)
clear s
```

## Control Pins

### In this section...

“Properties of Serial Port Control Pins” on page 17-54

“Signaling the Presence of Connected Devices” on page 17-54

“Controlling the Flow of Data: Handshaking” on page 17-57

### Properties of Serial Port Control Pins

As described in “Serial Port Signals and Pin Assignments” on page 17-6, 9-pin serial ports include six control pins. The following table shows properties associated with the serial port control pins.

#### Control Pin Properties

Property Name	Description
<code>DataTerminalReady</code>	State of the DTR pin
<code>FlowControl</code>	Data flow control method to use
<code>PinStatus</code>	State of the CD, CTS, DSR, and RI pins
<code>RequestToSend</code>	State of the RTS pin

### Signaling the Presence of Connected Devices

DTEs and DCEs often use the CD, DSR, RI, and DTR pins to indicate whether a connection is established between serial port devices. Once the connection is established, you can begin to write or read data.

To monitor the state of the CD, DSR, and RI pins, use the `PinStatus` property. To specify or monitor the state of the DTR pin, use the `DataTerminalReady` property.

The following example illustrates how these pins are used when two modems are connected to each other.

#### Example — Connecting Two Modems

This example connects two modems to each other via the same computer, and illustrates how to monitor the communication status for the computer-modem connections, and for

the modem-modem connection. The first modem is connected to COM1, while the second modem is connected to COM2.

- 1 Create the serial port objects — After the modems are powered on, the serial port object `s1` is created for the first modem, and the serial port object `s2` is created for the second modem.

```
s1 = serial('COM1');  
s2 = serial('COM2');
```

- 2 Connect to the devices — `s1` and `s2` are connected to the modems. Because the default value for the `ReadAsyncMode` property is `continuous`, data is asynchronously returned to the input buffers as soon as it is available from the modems.

```
fopen(s1)  
fopen(s2)
```

Because the default `DataTerminalReady` property value is `on`, the computer (data terminal) is now ready to exchange data with the modems. To verify that the modems (data sets) can communicate with the computer, examine the value of the `Data Set Ready` pin using the `PinStatus` property.

```
s1.Pinstatus  
ans =  
    CarrierDetect: 'off'  
    ClearToSend: 'on'  
    DataSetReady: 'on'  
    RingIndicator: 'off'
```

The value of the `DataSetReady` field is `on` because both modems were powered on before they were connected to the objects.

- 3 Configure properties — Both modems are configured for a baud rate of 2400 bits per second and a carriage return (CR) terminator.

```
s1.BaudRate = 2400;  
s1.Terminator = 'CR';  
s2.BaudRate = 2400;  
s2.Terminator = 'CR';
```

- 4 Write and read data — Write the `atd` command to the first modem. This command puts the modem “off the hook,” which is equivalent to manually lifting a phone receiver.

```
fprintf(s1, 'atd')
```

Write the `ata` command to the second modem. This command puts the modem in “answer mode,” which forces it to connect to the first modem.

```
fprintf(s2, 'ata')
```

After the two modems negotiate their connection, verify the connection status by examining the value of the Carrier Detect pin using the `PinStatus` property.

```
s1.PinStatus
ans =
    CarrierDetect: 'on'
      ClearToSend: 'on'
    DataSetReady: 'on'
    RingIndicator: 'off'
```

Verify the modem-modem connection by reading the descriptive message returned by the second modem.

```
s2.BytesAvailable
ans =
    25
out = fread(s2,25);
char(out) '
ans =
ata
CONNECT 2400/NONE
```

Now break the connection between the two modems by configuring the `DataTerminalReady` property to `off`. To verify the modems are disconnected, examine the Carrier Detect pin value.

```
s1.DataTerminalReady = 'off';
s1.PinStatus
ans =
    CarrierDetect: 'off'
      ClearToSend: 'on'
    DataSetReady: 'on'
    RingIndicator: 'off'
```

- 5 Disconnect and clean up — Disconnect the objects from the modems and remove the objects from memory and from the MATLAB workspace.



```
fclose([s1 s2])  
delete([s1 s2])  
clear s1 s2
```

## Controlling the Flow of Data: Handshaking

Data flow control or *handshaking* is a method used for communicating between a DCE and a DTE to prevent data loss during transmission. For example, suppose your computer can receive only a limited amount of data before it must be processed. As this limit is reached, a handshaking signal is transmitted to the DCE to stop sending data. When the computer can accept more data, another handshaking signal is transmitted to the DCE to resume sending data.

If supported by your device, you can control data flow using one of these methods:

- Hardware handshaking
- Software handshaking

---

**Note:** Although you might be able to configure your device for both hardware handshaking and software handshaking at the same time, MATLAB does not support this behavior.

---

To specify the data flow control method, use the `FlowControl` property. If `FlowControl` is `hardware`, hardware handshaking is used to control data flow. If `FlowControl` is `software`, software handshaking is used to control data flow. If `FlowControl` is `none`, no handshaking is used.

### Hardware Handshaking

Hardware handshaking uses specific serial port pins to control data flow. In most cases, these are the RTS and CTS pins. Hardware handshaking using these pins is described in “The RTS and CTS Pins” on page 17-8.

If `FlowControl` is `hardware`, the RTS and CTS pins are automatically managed by the DTE and DCE. To return the CTS pin value, use the `PinStatus` property. Configure or return the RTS pin value with the `RequestToSend` property.

---

**Note:** Some devices also use the DTR and DSR pins for handshaking. However, these pins are typically used to indicate that the system is ready for communication, and are not used to control data transmission. In MATLAB, hardware handshaking always uses the RTS and CTS pins.

---

If your device does not use hardware handshaking in the standard way, then you might need to manually configure the `RequestToSend` property. In this case, you should configure `FlowControl` to `none`. If `FlowControl` is hardware, then the `RequestToSend` value that you specify might not be honored. Refer to the device documentation to determine its specific pin behavior.

### Software Handshaking

Software handshaking uses specific ASCII characters to control data flow. These characters, known as Xon and Xoff (or XON and XOFF), are described in the following table.

#### Software Handshaking Characters

Character	Integer Value	Description
Xon	17	Resume data transmission
Xoff	19	Pause data transmission

When using software handshaking, the control characters are sent over the transmission line the same way as regular data. Therefore, only the TD, RD, and GND pins are needed.

The main disadvantage of software handshaking is that Xon or Xoff characters are not writable while numerical data is being written to the device. This is because numerical data might contain a 17 or 19, which makes it impossible to distinguish between the control characters and the data. However, you can write Xon or Xoff while data is being asynchronously read from the device because you are using both the TD and RD pins.

#### Example: Using Software Handshaking

Suppose you want to use software flow control with the example described in “Example — Reading Binary Data” on page 17-43. To do this, you must configure the oscilloscope and serial port object for software flow control.

```
fprintf(s, 'RS232:SOFTF ON')
```

```
s.FlowControl = 'software';
```

To pause data transfer, write the numerical value **19** to the device.

```
fwrite(s,19)
```

To resume data transfer, write the numerical value **17** to the device.

```
fwrite(s,17)
```

## Debugging: Recording Information to Disk

### In this section...

“Introduction” on page 17-60

“Recording Properties” on page 17-60

“Example: Introduction to Recording Information” on page 17-61

“Creating Multiple Record Files” on page 17-61

“Specifying a Filename” on page 17-61

“The Record File Format” on page 17-62

“Example: Recording Information to Disk” on page 17-63

### Introduction

Recording information to disk provides a permanent record of your serial port session, and is an easy way to debug your application. While the serial port object is connected to the device, you can record the following information to a disk file:

- The number of values written to the device, the number of values read from the device, and the data type of the values
- Data written to the device, and data read from the device
- Event information

### Recording Properties

You record information to a disk file with the `record` function. The following table shows the properties associated with recording information to disk.

#### Recording Properties

Property Name	Description
RecordDetail	Amount of information saved to a record file
RecordMode	Specify whether data and event information is saved to one record file or to multiple record files
RecordName	Name of the record file
RecordStatus	Indicate if data and event information are saved to a record file

## Example: Introduction to Recording Information

This example records the number of values written to and read from the device, and stores the information to the file `myfile.txt`.

```
s = serial('COM1');
fopen(s)
s.RecordName = 'myfile.txt';
record(s)
fprintf(s, '*IDN?')
idn = fscanf(s);
fprintf(s, 'RS232?')
rs232 = fscanf(s);
```

End the serial port session.

```
fclose(s)
delete(s)
clear s
```

To display `myfile.txt` at the command line, use the `type` command.

## Creating Multiple Record Files

When you initiate recording with the `record` function, the `RecordMode` property determines if a new record file is created or if new information is appended to an existing record file.

You can configure `RecordMode` to `overwrite`, `append`, or `index`. If `RecordMode` is `overwrite`, the record file is overwritten each time recording is initiated. If `RecordMode` is `append`, the new information is appended to the file specified by `RecordName`. If `RecordMode` is `index`, a different disk file is created each time recording is initiated. The rules for specifying a record filename are discussed in the next section.

## Specifying a Filename

You specify the name of the record file with the `RecordName` property. You can specify any value for `RecordName` — including a directory path — provided the filename is supported by your operating system. Additionally, if `RecordMode` is `index`, the filename follows these rules:

- Indexed filenames are identified by a number. This number precedes the filename extension and is increased by 1 for successive record files.
- If no number is specified as part of the initial filename, the first record file does not have a number associated with it. For example, if `RecordName` is `myfile.txt`, `myfile.txt` is the name of the first record file, `myfile01.txt` is the name of the second record file, and so on.
- `RecordName` is updated after the record file is closed.
- If the specified filename already exists, the existing file is overwritten.

## The Record File Format

The record file is an ASCII file that contains a record of one or more serial port sessions. You specify the amount of information saved to a record file with the `RecordDetail` property.

`RecordDetail` can be `compact` or `verbose`. A compact record file contains the number of values written to the device, the number of values read from the device, the data type of the values, and event information. A verbose record file contains the preceding information as well as the data transferred to and from the device.

Binary data with precision given by `uchar`, `schar`, `(u)int8`, `(u)int16`, or `(u)int32` is recorded using hexadecimal format. For example, if the integer value 255 is read from the instrument as a 16-bit integer, the hexadecimal value 00FF is saved in the record file. Single- and double-precision floating-point numbers are recorded as decimal values using the `%g` format, and as hexadecimal values using the format specified by the IEEE<sup>®</sup> Standard 754-1985 for Binary Floating-Point Arithmetic.

The IEEE floating-point format includes three components: the sign bit, the exponent field, and the significant field. Single-precision floating-point values consist of 32 bits. The value is given by

$$\text{value} = (-1)^{\text{sign}} (2^{\text{exp}-127}) (1.\text{significant})$$

Double-precision floating-point values consist of 64 bits. The value is given by

$$\text{value} = (-1)^{\text{sign}} (2^{\text{exp}-1023}) (1.\text{significant})$$

The floating-point format component, and the associated single-precision and double-precision bits are shown in the following table.

Component	Single-Precision Bits	Double-Precision Bits
sign	1	1
exp	2–9	2–12
significand	10–32	13–64

Bit 1 is the left-most bit as stored in the record file.

## Example: Recording Information to Disk

This example illustrates how to record information transferred between a serial port object and a Tektronix TDS 210 oscilloscope. Additionally, the structure of the resulting record file is presented.

- 1 Create the serial port object — Create the serial port object `s` associated with the serial port COM1.

```
s = serial('COM1');
```

- 2 Connect to the device — Connect `s` to the oscilloscope. Because the default value for the `ReadAsyncMode` property is `continuous`, data is asynchronously returned the input buffer as soon as it is available from the instrument.

```
fopen(s)
```

- 3 Configure property values — Configure `s` to record information to multiple disk files using the verbose format. Recording is then initiated with the first disk file defined as `WaveForm1.txt`.

```
s.RecordMode = 'index';
s.RecordDetail = 'verbose';
s.RecordName = 'WaveForm1.txt';
record(s)
```

- 4 Write and read data — The commands written to the instrument, and the data read from the instrument are recorded in the record file. For an explanation of the oscilloscope commands, see “Example — Writing and Reading Text Data” on page 17-41.

```
fprintf(s, '*IDN?')
idn = fscanf(s);
fprintf(s, 'MEASUREMENT:IMMED:SOURCE CH2')
fprintf(s, 'MEASUREMENT:IMMED:SOURCE?')
source = fscanf(s);
```

Read the peak-to-peak voltage with the `fread` function. Note that the data returned by `fread` is recorded using hex format.

```
fprintf(s, 'MEASUREMENT:MEAS1:TYPE PK2PK')
fprintf(s, 'MEASUREMENT:MEAS1:VALUE?')
ptop = fread(s,s.BytesAvailable);
```

Convert the peak-to-peak voltage to a character array.

```
char(ptop) '
ans =
2.0199999809E0
```

The recording state is toggled from `on` to `off`. Because the `RecordMode` value is `index`, the record filename is automatically updated.

```
record(s)
s.RecordStatus
ans =
off
s.RecordName
ans =
WaveForm2.txt
```

- 5 Disconnect and clean up — When you no longer need `s`, disconnect it from the instrument, and remove it from memory and from the MATLAB workspace.

```
fclose(s)
delete(s)
clear s
```

### The Record File Contents

The contents of the `WaveForm1.txt` record file are shown below. Because the `RecordDetail` property was `verbose`, the number of values, commands, and data were recorded. Note that data returned by the `fread` function is in hex format.

```
type WaveForm1.txt
```

Legend:

```
* - An event occurred.
> - A write operation occurred.
< - A read operation occurred.
1   Recording on 22-Jan-2000 at 11:21:21.575. Binary data in...
2   > 6 ascii values.
    *IDN?
```



```
3 < 56 ascii values.  
   TEKTRONIX,TDS 210,0,CF:91.1CT FV:v1.16 TDS2CM:CMV:v1.04  
4 > 29 ascii values.  
   MEASUREMENT:IMMED:SOURCE CH2  
5 > 26 ascii values.  
   MEASUREMENT:IMMED:SOURCE?  
6 < 4 ascii values.  
   CH2  
7 > 27 ascii values.  
   MEASUREMENT:MEAS1:TYPE PK2PK  
8 > 25 ascii values.  
   MEASUREMENT:MEAS1:VALUE?  
9 < 15 uchar values.  
   32 2e 30 31 39 39 39 39 38 30 39 45 30 0a  
10 Recording off.
```

## Save and Load

### In this section...

“Using save and load” on page 17-66

“Using Serial Port Objects on Different Platforms” on page 17-66

### Using save and load

Save serial port objects to a file, just as you would any workspace variable, using the `save` command. For example, suppose you create the serial port object `s` associated with the serial port COM1, configure several property values, and perform a write and read operation.

```
s = serial('COM1');
s.BaudRate = 19200;
s.Tag = 'My serial object';
fopen(s)
fprintf(s, '*IDN?')
out = fscanf(s);
```

To save the serial port object and the data read from the device to the file `myserial.mat`:

```
save myserial s out
```

---

**Note:** To save data and event information as text to a disk file, use the `record` function.

---

You can recreate `s` and `out` in the workspace using the `load` command.

```
load myserial
```

Values for read only properties are restored to their default values upon loading. For example, the `Status` property is restored to `closed`. Therefore, to use `s`, you must connect it to the device with the `fopen` function. To determine if a property is read only, examine its reference pages.

### Using Serial Port Objects on Different Platforms

If you save a serial port object from one platform, and then load that object on a different platform having different serial port names, you need to modify the `Port` property value.

For example, suppose you create the serial port object `s` associated with the serial port COM1 on a Microsoft Windows platform. If you want to save `s` for eventual use on a Linux platform, configure `Port` to an appropriate value such as `ttyS0` after the object is loaded.

## Disconnect and Clean Up

### In this section...

“Disconnect a Serial Port Object” on page 17-68

“Clean Up the MATLAB Environment” on page 17-68

### Disconnect a Serial Port Object

When you no longer need to communicate with the device, disconnect it from the serial port object with the `fclose` function.

```
fclose(s)
```

Examine the `Status` property to verify that the serial port object and the device are disconnected.

```
s.Status  
ans =  
closed
```

After `fclose` is issued, the serial port associated with `s` is available. Now connect another serial port object to it using `fopen`.

### Clean Up the MATLAB Environment

When the serial port object is no longer needed, remove it from memory with the `delete` function.

```
delete(s)
```

Before using `delete`, disconnect the serial port object from the device with the `fclose` function.

A deleted serial port object is *invalid*, which means that you cannot connect it to the device. In this case, remove the object from the MATLAB workspace. To remove serial port objects and other variables from the MATLAB workspace, use the `clear` command.

```
clear s
```

Use `clear` on a serial port object that is still connected to a device to remove the object from the workspace but leave it connected to the device. Restore cleared objects to MATLAB with the `instrfind` function.

## Property Reference

In this section...
“The Property Reference Page Format” on page 17-70
“Serial Port Object Properties” on page 17-70

### The Property Reference Page Format

Each serial port property description contains some or all of this information:

- The property name
- A description of the property
- The property characteristics, including:
  - Read only — The condition under which the property is read only

A property can be read-only always, never, while the serial port object is open, or while the serial port object is recording. You can configure a property value using the `set` function or dot notation. You can return the current property value using the `get` function or dot notation.

- Data type — the property data type

This is the data type you use when specifying a property value.

- Valid property values including the default value

When property values are given by a predefined list, the default value is usually indicated by `{}`.

- An example using the property
- Related properties and functions

### Serial Port Object Properties

The serial port object properties are briefly described below, and organized into categories based on how they are used. Following this section the properties are listed alphabetically and described in detail.

<b>Communications Properties</b>	
BaudRate	Rate at which bits are transmitted
DataBits	Number of data bits to transmit
Parity	Type of parity checking
StopBits	Number of bits used to indicate the end of a byte
Terminator	Terminator character

<b>Write Properties</b>	
BytesToOutput	Number of bytes currently in the output buffer
OutputBufferSize	Size of the output buffer in bytes
Timeout	Waiting time to complete a read or write operation
TransferStatus	Indicate if an asynchronous read or write operation is in progress
ValuesSent	Total number of values written to the device

<b>Read Properties</b>	
BytesAvailable	Number of bytes available in the input buffer
InputBufferSize	Size of the input buffer in bytes
ReadAsyncMode	Specify whether an asynchronous read operation is continuous or manual
Timeout	Waiting time to complete a read or write operation
TransferStatus	Indicate if an asynchronous read or write operation is in progress
ValuesReceived	Total number of values read from the device

<b>Callback Properties</b>	
BreakInterruptFcn	Callback function to execute when a break-interrupt event occurs
BytesAvailableFcn	Callback function to execute when a specified number of bytes is available in the input buffer, or a terminator is read

<b>Callback Properties</b>	
BytesAvailableFcnCount	Number of bytes that must be available in the input buffer to generate a bytes-available event
BytesAvailableFcnMode	Specify if the bytes-available event is generated after a specified number of bytes is available in the input buffer, or after a terminator is read
ErrorFcn	Callback function to execute when an error event occurs
OutputEmptyFcn	Callback function to execute when the output buffer is empty
PinStatusFcn	Callback function to execute when the CD, CTS, DSR, or RI pins change state
TimerFcn	Callback function to execute when a predefined period of time passes
TimerPeriod	Period of time between timer events

<b>Control Pin Properties</b>	
DataTerminalReady	State of the DTR pin
FlowControl	Data flow control method to use
PinStatus	State of the CD, CTS, DSR, and RI pins
RequestToSend	State of the RTS pin

<b>Recording Properties</b>	
RecordDetail	Amount of information saved to a record file
RecordMode	Specify whether data and event information are saved to one record file or to multiple record files
RecordName	Name of the record file
RecordStatus	Indicate if data and event information are saved to a record file

<b>General Purpose Properties</b>	
ByteOrder	Order in which the device stores bytes
Name	Descriptive name for the serial port object



---

<b>General Purpose Properties</b>	
Port	Platform-specific serial port name
Status	Indicate if the serial port object is connected to the device
Tag	Label to associate with a serial port object
Type	Object type
UserData	Data you want to associate with a serial port object

## **Properties — Alphabetical List**

# BaudRate

Specify the rate at which bits are transmitted

## Description

You configure **BaudRate** as bits per second. The transferred bits include the start bit, the data bits, the parity bit (if used), and the stop bits. However, only the data bits are stored.

The baud rate is the rate at which information is transferred in a communication channel. In the serial port context, “9600 baud” means that the serial port is capable of transferring a maximum of 9600 bits per second. If the information unit is one baud (one bit), the bit rate and the baud rate are identical. If one baud is given as 10 bits, (for example, eight data bits plus two framing bits), the bit rate is still 9600 but the baud rate is 9600/10, or 960. You always configure **BaudRate** as bits per second. Therefore, in the previous example, set **BaudRate** to 9600.

---

**Note:** Both the computer and the peripheral device must be configured to the same baud rate before you can successfully read or write data.

---

Standard baud rates include 110, 300, 600, 1200, 2400, 4800, 9600, 14400, 19200, 38400, 57600, 115200, 128000 and 256000 bits per second. To display the supported baud rates for the serial ports on your platform, see “Finding Serial Port Information for Your Platform” on page 17-13.

## Characteristics

Read only	Never
Data type	Double

## Values

The default value is **9600**.

## **See Also**

### **Properties**

DataBits, Parity, StopBits

# BreakInterruptFcn

Specify the callback function to execute when a break-interrupt event occurs

## Description

You configure `BreakInterruptFcn` to execute a callback function when a break-interrupt event occurs. A break-interrupt event is generated by the serial port when the received data is in an off (space) state longer than the transmission time for one byte.

---

**Note:** A break-interrupt event can be generated at any time during the serial port session.

---

If the `RecordStatus` property value is `on`, and a break-interrupt event occurs, the record file records this information:

- The event type as `BreakInterrupt`
- The time the event occurred using the format `day-month-year hour:minute:second:millisecond`

To learn how to create a callback function, see “Create and Execute Callback Functions” on page 17-51.

## Characteristics

Read only	Never
Data type	Callback function

## Values

The default value is an empty string.

## **See Also**

### **Functions**

record

### **Properties**

RecordStatus

# ByteOrder

Specify the byte order of the device

## Description

You configure `ByteOrder` to be `littleEndian` or `bigEndian`. If `ByteOrder` is `littleEndian`, the device stores the first byte in the first memory address. If `ByteOrder` is `bigEndian`, the device stores the last byte in the first memory address.

For example, suppose the hexadecimal value `4F52` is to be stored in device memory. Because this value consists of two bytes, `4F` and `52`, two memory locations are used. Using big-endian format, `4F` is stored first in the lower storage address. Using little-endian format, `52` is stored first in the lower storage address.

---

**Note:** Configure `ByteOrder` to the appropriate value for your device before performing a read or write operation. Refer to your device documentation for information about the order in which it stores bytes.

---

## Characteristics

Read only	Never
Data type	String

## Values

<code>{littleEndian}</code>	The byte order of the device is little-endian.
<code>bigEndian</code>	The byte order of the device is big-endian.

## See Also

### Properties

Status

## BytesAvailable

Number of bytes available in the input buffer

### Description

`BytesAvailable` indicates the number of bytes currently available to be read from the input buffer. The property value is continuously updated as the input buffer is filled, and is set to 0 after the `fopen` function is issued.

You can make use of `BytesAvailable` only when reading data asynchronously. This is because when reading data synchronously, control is returned to the MATLAB command line only after the input buffer is empty. Therefore, the `BytesAvailable` value is always 0. To learn how to read data asynchronously, see “Reading Text Data” on page 17-38.

The `BytesAvailable` value can range from zero to the size of the input buffer. Use the `InputBufferSize` property to specify the size of the input buffer. Use the `ValuesReceived` property to return the total number of values read.

### Characteristics

Read only	Always
Data type	Double

### Values

The default value is 0.

### See Also

#### Functions

`fopen`



## **Properties**

InputBufferSize, TransferStatus, ValuesReceived

## BytesAvailableFcn

Specify the callback function to execute when a specified number of bytes is available in the input buffer, or a terminator is read

### Description

You configure `BytesAvailableFcn` to execute a callback function when a bytes-available event occurs. A bytes-available event occurs when the number of bytes specified by the `BytesAvailableFcnCount` property is available in the input buffer, or after a terminator is read, as determined by the `BytesAvailableFcnMode` property.

---

**Note:** A bytes-available event can be generated only for asynchronous read operations.

---

If the `RecordStatus` property value is `on`, and a bytes-available event occurs, the record file records this information:

- The event type as `BytesAvailable`
- The time the event occurred using the format day-month-year hour:minute:second:millisecond

To learn how to create a callback function, see “Create and Execute Callback Functions” on page 17-51.

### Characteristics

Read only	Never
Data type	Callback function

### Values

The default value is an empty string.

## Example

Create the serial port object `s` for a Tektronix TDS 210 two-channel oscilloscope connected to the serial port COM1.

```
s = serial('COM1');
```

Configure `s` to execute the callback function `instrcallback` when 40 bytes are available in the input buffer.

```
s.BytesAvailableFcnCount = 40;  
s.BytesAvailableFcnMode = 'byte';  
s.BytesAvailableFcn = @instrcallback;
```

Connect `s` to the oscilloscope.

```
fopen(s)
```

Write the `*IDN?` command, which instructs the scope to return identification information. Because the default value for the `ReadAsyncMode` property is `continuous`, data is read as soon as it is available from the instrument.

```
fprintf(s, '*IDN?')
```

MATLAB displays:

```
BytesAvailable event occurred at 18:33:35 for the object:  
Serial-COM1.
```

56 bytes are read and `instrcallback` is called once. The resulting display is shown above.

```
s.BytesAvailable  
ans =  
    56
```

Suppose you remove 25 bytes from the input buffer and then issue the `MEASUREMENT?` command, which instructs the scope to return its measurement settings.

```
out = fscanf(s, '%c', 25);  
fprintf(s, 'MEASUREMENT?')
```

MATLAB displays:

```
BytesAvailable event occurred at 18:33:48 for the object:
```

Serial-COM1.

BytesAvailable event occurred at 18:33:48 for the object:  
Serial-COM1.

There are now 102 bytes in the input buffer, 31 of which are left over from the \*IDN? command. `instrcallback` is called twice—once when 40 bytes are available and once when 80 bytes are available.

```
s.BytesAvailable  
ans =  
    102
```

## See Also

### Functions

`record`

### Properties

`BytesAvailableFcnCount`, `BytesAvailableFcnMode`, `RecordStatus`, `Terminator`, `TransferStatus`

# BytesAvailableFcnCount

Specify the number of bytes that must be available in the input buffer to generate a bytes-available event

## Description

You configure `BytesAvailableFcnCount` to the number of bytes that must be available in the input buffer before a bytes-available event is generated.

Use the `BytesAvailableFcnMode` property to specify whether the bytes-available event occurs after a certain number of bytes are available or after a terminator is read.

The bytes-available event executes the callback function specified for the `BytesAvailableFcn` property.

You can configure `BytesAvailableFcnCount` only when the object is disconnected from the device. You disconnect an object with the `fclose` function. A disconnected object has a `Status` property value of `closed`.

## Characteristics

Read only	While open
Data type	Double

## Values

The default value is 48.

## See Also

### Functions

`fclose`

## **Properties**

BytesAvailableFcn, BytesAvailableFcnMode, Status

## BytesAvailableFcnMode

Specify if the bytes-available event is generated after a specified number of bytes is available in the input buffer, or after a terminator is read

### Description

You can configure `BytesAvailableFcnMode` to be `terminator` or `byte`. If `BytesAvailableFcnMode` is `terminator`, a bytes-available event occurs when the terminator specified by the `Terminator` property is reached. If `BytesAvailableFcnMode` is `byte`, a bytes-available event occurs when the number of bytes specified by the `BytesAvailableFcnCount` property is available.

The bytes-available event executes the callback function specified for the `BytesAvailableFcn` property.

You can configure `BytesAvailableFcnMode` only when the object is disconnected from the device. You disconnect an object with the `fclose` function. A disconnected object has a `Status` property value of `closed`.

### Characteristics

Read only	While open
Data type	String

### Values

<code>{terminator}</code>	A bytes-available event is generated when the terminator is read.
<code>byte</code>	A bytes-available event is generated when the specified number of bytes are available.

## **See Also**

### **Functions**

`fclose`

### **Properties**

`BytesAvailableFcn`, `BytesAvailableFcnCount`, `Status`, `Terminator`



# BytesToOutput

Number of bytes currently in the output buffer

## Description

BytesToOutput indicates the number of bytes currently in the output buffer waiting to be written to the device. The property value is continuously updated as the output buffer is filled and emptied, and is set to 0 after the `fopen` function is issued.

You can make use of BytesToOutput only when writing data asynchronously. This is because when writing data synchronously, control is returned to the MATLAB command line only after the output buffer is empty. Therefore, the BytesToOutput value is always 0. To learn how to write data asynchronously, see “Writing Text Data” on page 17-32.

Use the ValuesSent property to return the total number of values written to the device.

---

**Note:** If you attempt to write out more data than can fit in the output buffer, an error is returned and BytesToOutput is 0. Specify the size of the output buffer with the OutputBufferSize property.

---

## Characteristics

Read only	Always
Data type	Double

## Values

The default value is 0.

## **See Also**

### **Functions**

fopen

### **Properties**

OutputBufferSize, TransferStatus, ValuesSent

## DataBits

Number of data bits to transmit

### Description

You can configure **DataBits** to be 5, 6, 7, or 8. Data is transmitted as a series of five, six, seven, or eight bits with the least significant bit sent first. At least seven data bits are required to transmit ASCII characters. Eight bits are required to transmit binary data. Five and six bit data formats are used for specialized communications equipment.

---

**Note:** Both the computer and the peripheral device must be configured to transmit the same number of data bits.

---

In addition to the data bits, the serial data format consists of a start bit, one or two stop bits, and possibly a parity bit. You specify the number of stop bits with the **StopBits** property, and the type of parity checking with the **Parity** property.

To display the supported number of data bits for the serial ports on your platform, see “Finding Serial Port Information for Your Platform” on page 17-13.

### Characteristics

Read only	Never
Data type	Double

### Values

**DataBits** can be 5, 6, 7, or 8. The default value is 8.

## **See Also**

### **Properties**

Parity, StopBits

# DataTerminalReady

State of the DTR pin

## Description

You can configure `DataTerminalReady` to be on or off. If `DataTerminalReady` is on, the Data Terminal Ready (DTR) pin is asserted. If `DataTerminalReady` is off, the DTR pin is unasserted.

In normal usage, the DTR and Data Set Ready (DSR) pins work together, and are used to signal if devices are connected and powered. However, there is nothing in the RS-232 standard that states the DTR pin must be used in any specific way. For example, DTR and DSR might be used for handshaking. You should refer to your device documentation to determine its specific pin behavior.

You can return the value of the DSR pin with the `PinStatus` property. Handshaking is described in “Controlling the Flow of Data: Handshaking” on page 17-57.

## Characteristics

Read only	Never
Data type	String

## Values

{on}	The DTR pin is asserted.
off	The DTR pin is unasserted.

## See Also

### Properties

`FlowControl`, `PinStatus`

## ErrorFcn

Specify the callback function to execute when an error event occurs

### Description

You configure `ErrorFcn` to execute a callback function when an error event occurs.

---

**Note:** An error event is generated only for asynchronous read and write operations.

---

An error event is generated when a time-out occurs. A time-out occurs if a read or write operation does not successfully complete within the time specified by the `Timeout` property. An error event is not generated for configuration errors such as setting an invalid property value.

If the `RecordStatus` property value is `on`, and an error event occurs, the record file records this information:

- The event type as `Error`
- The error message
- The time the event occurred using the format `day-month-year hour:minute:second:millisecond`

To learn how to create a callback function, see “Create and Execute Callback Functions” on page 17-51.

### Characteristics

Read only	Never
Data type	Callback function

### Values

The default value is an empty string.

## See Also

### Functions

record

### Properties

RecordStatus, Timeout

## FlowControl

Data flow control method to use

### Description

You can configure `FlowControl` to be `none`, `hardware`, or `software`. If `FlowControl` is `none`, data flow control (handshaking) is not used. If `FlowControl` is `hardware`, hardware handshaking is used to control data flow. If `FlowControl` is `software`, software handshaking is used to control data flow.

Hardware handshaking typically utilizes the Request to Send (RTS) and Clear to Send (CTS) pins to control data flow. Software handshaking uses control characters (Xon and Xoff) to control data flow. For more information about handshaking, see “Controlling the Flow of Data: Handshaking” on page 17-57.

You can return the value of the CTS pin with the `PinStatus` property. You can specify the value of the RTS pin with the `RequestToSend` property. However, if `FlowControl` is `hardware`, and you specify a value for `RequestToSend`, that value might not be honored.

---

**Note:** Although you might be able to configure your device for both hardware handshaking and software handshaking at the same time, MATLAB does not support this behavior.

---

### Characteristics

Read only	Never
Data type	String

### Values

{none}	No flow control is used.
hardware	Hardware flow control is used.



software	Software flow control is used.
----------	--------------------------------

## See Also

### Properties

PinStatus, RequestToSend

## InputBufferSize

Size of the input buffer in bytes

### Description

You configure `InputBufferSize` as the total number of bytes that can be stored in the input buffer during a read operation.

A read operation is terminated if the amount of data stored in the input buffer equals the `InputBufferSize` value. You can read text data with the `fgetl`, `fget`, or `fscanf` functions. You can read binary data with the `fread` function.

You can configure `InputBufferSize` only when the serial port object is disconnected from the device. You disconnect an object with the `fclose` function. A disconnected object has a `Status` property value of `closed`.

If you configure `InputBufferSize` while there is data in the input buffer, that data is flushed.

### Characteristics

Read only	While open
Data type	Double

### Values

The default value is 512.

### See Also

#### Functions

`fclose`, `fgetl`, `fgets`, `fopen`, `fread`, `fscanf`

## Properties

Status

## Name

Descriptive name for the serial port object

## Description

You configure **Name** to be a descriptive name for the serial port object.

When you create a serial port object, a descriptive name is automatically generated and stored in **Name**. This name is given by concatenating the word “Serial” with the serial port specified in the `serial` function. However, you can change the value of **Name** at any time.

The serial port is given by the **Port** property. If you modify this property value, then **Name** is automatically updated to reflect that change.

## Characteristics

Read only	Never
Data type	String

## Values

**Name** is automatically defined when the serial port object is created.

## Example

Suppose you create a serial port object associated with the serial port COM1.

```
s = serial('COM1');
```

**s** is automatically assigned a descriptive name.

```
s.Name  
ans =
```

Serial-COM1

## **See Also**

### **Functions**

serial

## ObjectVisibility

Control access to serial port object

### Description

The `ObjectVisibility` property provides a way for application developers to prevent end-user access to the serial port objects created by their applications. When an object's `ObjectVisibility` property is set to `off`, `instrfind` does not return or delete that object.

Objects that are not visible are still valid. If you have access to the object (for example, from within the file that creates it), you can set and get its properties and pass it to any function that operates on serial port objects.

### Characteristics

Usage	Any serial port object
Read only	Never
Data type	String

### Values

{on}	Object is visible to <code>instrfind</code> .
off	Object is not visible from the command line (except by <code>instrfindall</code> ).

### Examples

The following statement creates a serial port object with its `ObjectVisibility` property set to `Off`:

```
s = serial('COM1', 'ObjectVisibility', 'off');
```

```
instrfind
ans =
     []
```

However, because the hidden object is in the workspace (**s**), you can access it.

```
get(s, 'ObjectVisibility')
ans =
    off
```

## See Also

### Functions

`instrfind`, `instrfindall`

## OutputBufferSize

Size of the output buffer in bytes

### Description

You configure `OutputBufferSize` as the total number of bytes that can be stored in the output buffer during a write operation.

An error occurs if the output buffer cannot hold all the data to be written. You write text data with the `fprintf` function. You write binary data with the `fwrite` function.

You can configure `OutputBufferSize` only when the serial port object is disconnected from the device. You disconnect an object with the `fclose` function. A disconnected object has a `Status` property value of `closed`.

### Characteristics

Read only	While open
Data type	Double

### Values

The default value is 512.

### See Also

#### Functions

`fprintf`, `fwrite`

#### Properties

`Status`



# OutputEmptyFcn

Specify the callback function to execute when the output buffer is empty

## Description

You configure OutputEmptyFcn to execute a callback function when an output-empty event occurs. An output-empty event is generated when the last byte is sent from the output buffer to the device.

---

**Note:** An output-empty event can be generated only for asynchronous write operations.

---

If the RecordStatus property value is on, and an output-empty event occurs, the record file records this information:

- The event type as OutputEmpty
- The time the event occurred using the format day-month-year  
hour:minute:second:millisecond

To learn how to create a callback function, see “Create and Execute Callback Functions” on page 17-51.

## Characteristics

Read only	Never
Data type	Callback function

## Values

The default value is an empty string.

## **See Also**

### **Functions**

record

### **Properties**

RecordStatus

# Parity

Specify the type of parity checking

## Description

You can configure **Parity** to be **none**, **odd**, **even**, **mark**, or **space**. If **Parity** is **none**, parity checking is not performed and the parity bit is not transmitted. If **Parity** is **odd**, the number of mark bits (1s) in the data is counted, and the parity bit is asserted or unasserted to obtain an odd number of mark bits. If **Parity** is **even**, the number of mark bits in the data is counted, and the parity bit is asserted or unasserted to obtain an even number of mark bits. If **Parity** is **mark**, the parity bit is asserted. If **Parity** is **space**, the parity bit is unasserted.

Parity checking can detect errors of one bit only. An error in two bits might cause the data to have a seemingly valid parity, when in fact it is incorrect. For more information about parity checking, see “The Parity Bit” on page 17-12.

In addition to the parity bit, the serial data format consists of a start bit, between five and eight data bits, and one or two stop bits. You specify the number of data bits with the **DataBits** property, and the number of stop bits with the **StopBits** property.

## Characteristics

Read only	Never
Data type	String

## Values

{none}	No parity checking
odd	Odd parity checking
even	Even parity checking
mark	Mark parity checking

space	Space parity checking
-------	-----------------------

## See Also

### Properties

DataBits, StopBits

## PinStatus

State of the CD, CTS, DSR, and RI pins

### Description

`PinStatus` is a structure array that contains the fields `CarrierDetect`, `ClearToSend`, `DataSetReady` and `RingIndicator`. These fields indicate the state of the Carrier Detect (CD), Clear to Send (CTS), Data Set Ready (DSR) and Ring Indicator (RI) pins, respectively. For more information about these pins, see “Serial Port Signals and Pin Assignments” on page 17-6.

`PinStatus` can be `on` or `off` for any of these fields. A value of `on` indicates the associated pin is asserted. A value of `off` indicates the associated pin is unasserted. A pin status event occurs when any of these pins changes its state. A pin status event executes the call back function specified by `PinStatusFcn`.

In normal usage, the Data Terminal Ready (DTR) and DSR pins work together, while the Request to Send (RTS) and CTS pins work together. You can specify the state of the DTR pin with the `DataTerminalReady` property. You can specify the state of the RTS pin with the `RequestToSend` property.

For an example that uses `PinStatus`, see “Example — Connecting Two Modems” on page 17-54.

### Characteristics

Read only	Always
Data type	Structure

### Values

<code>off</code>	The associated pin is unasserted.
<code>on</code>	The associated pin is asserted.

The default value is device dependent.

### **See Also**

### **Properties**

DataTerminalReady, PinStatusFcn, RequestToSend

# PinStatusFcn

Specify the callback function to execute when the CD, CTS, DSR, or RI pins change state

## Description

You configure `PinStatusFcn` to execute a callback function when a pin status event occurs. A pin status event occurs when the Carrier Detect (CD), Clear to Send (CTS), Data Set Ready (DSR) or Ring Indicator (RI) pin changes state. A serial port pin changes state when it is asserted or unasserted. Information about the state of these pins is recorded in the `PinStatus` property.

---

**Note:** A pin status event can be generated at any time during the serial port session.

---

If the `RecordStatus` property value is `on`, and a pin status event occurs, the record file records this information:

- The event type as `PinStatus`
- The pin that changed its state, and the pin state as either `on` or `off`
- The time the event occurred using the format day-month-year hour:minute:second:millisecond

To learn how to create a callback function, see “Create and Execute Callback Functions” on page 17-51.

## Characteristics

Read only	Never
Data type	Callback function

## Values

The default value is an empty string.

## **See Also**

### **Functions**

record

### **Properties**

PinStatus, RecordStatus



# Port

Specify the platform-specific serial port name

## Description

You configure `Port` to be the name of a serial port on your platform. `Port` specifies the physical port associated with the object and the device.

When you create a serial port object, `Port` is automatically assigned the port name specified for the `serial` function.

You can configure `Port` only when the object is disconnected from the device. You disconnect an object with the `fclose` function. A disconnected object has a `Status` property value of `closed`.

## Characteristics

Read only	While open
Data type	String

## Values

The `Port` value is determined when the serial port object is created.

## Example

Suppose you create a serial port object associated with serial port `COM1`.

```
s = serial('COM1');
```

The value of the `Port` property is `COM1`.

```
s.Port  
ans =
```

COM1

## **See Also**

### **Functions**

`fclose`, `serial`

### **Properties**

`Name`, `Status`

# ReadAsyncMode

Specify whether an asynchronous read operation is continuous or manual

## Description

You can configure `ReadAsyncMode` to be `continuous` or `manual`. If `ReadAsyncMode` is `continuous`, the serial port object continuously queries the device to determine if data is available to be read. If data is available, it is automatically read and stored in the input buffer. If issued, the `readasync` function is ignored.

If `ReadAsyncMode` is `manual`, the object does not query the device to determine if data is available to be read. Instead, you must manually issue the `readasync` function to perform an asynchronous read operation. Because `readasync` checks for the terminator, this function can be slow. To increase speed, configure `ReadAsyncMode` to `continuous`.

---

**Note:** If the device is ready to transmit data, it will do so regardless of the `ReadAsyncMode` value. Therefore, if `ReadAsyncMode` is `manual` and a read operation is not in progress, data might be lost. To guarantee that all transmitted data is stored in the input buffer, you should configure `ReadAsyncMode` to `continuous`.

---

To determine the amount of data available in the input buffer, use the `BytesAvailable` property. For either `ReadAsyncMode` value, you can bring data into the MATLAB workspace with one of the synchronous read functions such as `fscanf`, `fgetl`, `fgets`, or `fread`.

## Characteristics

Read only	Never
Data type	String

## Values

{ <code>continuous</code> }	Continuously query the device to determine if data is available to be read.
-----------------------------	---

manual	Manually read data from the device using the <code>readasync</code> function.
--------	---

## See Also

### Functions

`fgetl`, `fgets`, `fread`, `fscanf`, `readasync`

### Properties

`BytesAvailable`, `InputBufferSize`

# RecordDetail

Specify the amount of information saved to a record file

## Description

You can configure `RecordDetail` to be `compact` or `verbose`. If `RecordDetail` is `compact`, the number of values written to the device, the number of values read from the device, the data type of the values, and event information are saved to the record file. If `RecordDetail` is `verbose`, the data written to the device, and the data read from the device are also saved to the record file.

The event information saved to a record file is shown in the table, `Event Information`. The verbose record file structure is shown in “`Example: Recording Information to Disk`” on page 17-63.

## Characteristics

Read only	Never
Data type	String

## Values

<code>{compact}</code>	The number of values written to the device, the number of values read from the device, the data type of the values, and event information are saved to the record file.
<code>verbose</code>	The data written to the device, and the data read from the device are also saved to the record file.

## See Also

### Functions

`record`

## **Properties**

RecordMode, RecordName, RecordStatus

## RecordMode

Specify whether data and event information are saved to one record file or to multiple record files

### Description

You can configure `RecordMode` to be `overwrite`, `append`, or `index`. If `RecordMode` is `overwrite`, the record file is overwritten each time recording is initiated. If `RecordMode` is `append`, data is appended to the record file each time recording is initiated. If `RecordMode` is `index`, a different record file is created each time recording is initiated, each with an indexed filename.

You can configure `RecordMode` only when the object is not recording. You terminate recording with the `record` function. A object that is not recording has a `RecordStatus` property value of `off`.

You specify the record filename with the `RecordName` property. The indexed filename follows a prescribed set of rules. For a description of these rules, see “Specifying a Filename” on page 17-61.

### Characteristics

Read only	While recording
Data type	String

### Values

<code>{overwrite}</code>	The record file is overwritten.
<code>append</code>	Data is appended to an existing record file.
<code>index</code>	A different record file is created, each with an indexed filename.

### Example

Suppose you create the serial port object `s` associated with the serial port COM1.

```
s = serial('COM1');  
fopen(s)
```

Specify the record filename with the `RecordName` property, configure `RecordMode` to `index`, and initiate recording.

```
s.RecordName = 'MyRecord.txt';  
s.RecordMode = 'index';  
record(s)
```

The record filename is automatically updated with an indexed filename after recording is turned off.

```
record(s, 'off')  
s.RecordName  
ans =  
MyRecord01.txt
```

Disconnect `s` from the peripheral device, remove `s` from memory, and remove `s` from the MATLAB workspace.

```
fclose(s)  
delete(s)  
clear s
```

## See Also

### Functions

`record`

### Properties

`RecordDetail`, `RecordName`, `RecordStatus`



# RecordName

Name of the record file

## Description

You configure `RecordName` to be the name of the record file. You can specify any value for `RecordName` - including a directory path - provided the file name is supported by your operating system.

MATLAB software supports any file name supported by your operating system. However, if you access the file with a MATLAB command, you might need to specify the file name using single quotes. For example, suppose you name the record file `My Record.txt`. To type this file at the MATLAB command line, you must include the name in quotes.

```
type('My Record.txt')
```

You can specify whether data and event information are saved to one disk file or to multiple disk files with the `RecordMode` property. If `RecordMode` is `index`, the filename follows a prescribed set of rules. For a description of these rules, see “Specifying a Filename” on page 17-61.

You can configure `RecordName` only when the object is not recording. You terminate recording with the `record` function. An object that is not recording has a `RecordStatus` property value of `off`.

## Characteristics

Read only	While recording
Data type	String

## Values

The default record filename is `record.txt`.

## **See Also**

### **Functions**

record

### **Properties**

RecordDetail, RecordMode, RecordStatus

# RecordStatus

Indicate if data and event information are saved to a record file

## Description

You can configure `RecordStatus` to be `off` or `on` with the `record` function. If `RecordStatus` is `off`, then data and event information are not saved to a record file. If `RecordStatus` is `on`, then data and event information are saved to the record file specified by `RecordName`.

Use the `record` function to initiate or complete recording. `RecordStatus` is automatically configured to reflect the recording state.

For more information about recording to a disk file, see “Debugging: Recording Information to Disk” on page 17-60.

## Characteristics

Read only	Always
Data type	String

## Values

<code>{off}</code>	Data and event information are not written to a record file.
<code>on</code>	Data and event information are written to a record file.

## See Also

### Functions

`record`

## **Properties**

RecordDetail, RecordMode, RecordName

# RequestToSend

State of the RTS pin

## Description

You can configure `RequestToSend` to be `on` or `off`. If `RequestToSend` is `on`, the Request to Send (RTS) pin is asserted. If `RequestToSend` is `off`, the RTS pin is unasserted.

In normal usage, the RTS and Clear to Send (CTS) pins work together, and are used as standard handshaking pins for data transfer. In this case, RTS and CTS are automatically managed by the DTE and DCE. However, there is nothing in the RS-232 standard that requires the RTS pin must be used in any specific way. Therefore, if you manually configure the `RequestToSend` value, it is probably for nonstandard operations.

If your device does not use hardware handshaking in the standard way, and you need to manually configure `RequestToSend`, configure the `FlowControl` property to `none`. Otherwise, the `RequestToSend` value that you specify might not be honored. Refer to your device documentation to determine its specific pin behavior.

You can return the value of the CTS pin with the `PinStatus` property. Handshaking is described in “Controlling the Flow of Data: Handshaking” on page 17-57.

## Characteristics

Read only	Never
Data type	String

## Values

<code>{on}</code>	The RTS pin is asserted.
<code>off</code>	The RTS pin is unasserted.

## **See Also**

### **Properties**

FlowControl, PinStatus

## Status

Indicate if the serial port object is connected to the device

## Description

Status can be `open` or `closed`. If Status is `closed`, the serial port object is not connected to the device. If Status is `open`, the serial port object is connected to the device.

Before you can write or read data, you must connect the serial port object to the device with the `fopen` function. Use the `fclose` function to disconnect a serial port object from the device.

## Characteristics

Read only	Always
Data type	String

## Values

<code>{closed}</code>	The serial port object is not connected to the device.
<code>open</code>	The serial port object is connected to the device.

## See Also

### Functions

`fclose`, `fopen`

## StopBits

Number of bits used to indicate the end of a byte

### Description

You can configure `StopBits` to be 1, 1.5, or 2. If `StopBits` is 1, one stop bit is used to indicate the end of data transmission. If `StopBits` is 2, two stop bits are used to indicate the end of data transmission. If `StopBits` is 1.5, the stop bit is transferred for 150% of the normal time used to transfer one bit.

---

**Note:** Both the computer and the peripheral device must be configured to transmit the same number of stop bits.

---

In addition to the stop bits, the serial data format consists of a start bit, between five and eight data bits, and possibly a parity bit. You specify the number of data bits with the `DataBits` property, and the type of parity checking with the `Parity` property.

### Characteristics

Read only	Never
Data type	Double

### Values

{1}	One stop bit is transmitted to indicate the end of a byte.
1.5	The stop bit is transferred for 150% of the normal time used to transfer one bit.
2	Two stop bits are transmitted to indicate the end of a byte.



## See Also

### Properties

DataBits, Parity

## Tag

Label to associate with a serial port object

## Description

You configure `Tag` to be a string value that uniquely identifies a serial port object.

`Tag` is particularly useful when constructing programs that would otherwise need to define the serial port object as a global variable, or pass the object as an argument between callback routines.

You can return the serial port object with the `instrfind` function by specifying the `Tag` property value.

## Characteristics

Read only	Never
Data type	String

## Values

The default value is an empty string.

## Example

Suppose you create a serial port object associated with the serial port COM1.

```
s = serial('COM1');  
fopen(s)
```

You can assign `s` a unique label using `Tag`.

```
set(s, 'Tag', 'MySerialObj')
```

You can access `s` in the MATLAB workspace or in a file using the `instrfind` function and the `Tag` property value.

```
s1 = instrfind('Tag', 'MySerialObj');
```

## See Also

### Functions

`instrfind`

## Terminator

Terminator character

### Description

You can configure `Terminator` to an integer value ranging from 0 to 127, which represents the ASCII code for the character, or you can configure `Terminator` to the ASCII character. For example, to configure `Terminator` to a carriage return, specify the value to be `CR` or 13. To configure `Terminator` to a linefeed, specify the value to be `LF` or 10. You can also set `Terminator` to `CR/LF` or `LF/CR`. If `Terminator` is `CR/LF`, the terminator is a carriage return followed by a line feed. If `Terminator` is `LF/CR`, the terminator is a linefeed followed by a carriage return. Note that there are no integer equivalents for these two values. Additionally, you can set `Terminator` to a 1-by-2 cell array. The first element of the cell is the read terminator and the second element of the cell array is the write terminator.

When performing a write operation using the `fprintf` function, all occurrences of `\n` are replaced with the `Terminator` property value. Note that `%s\n` is the default format for `fprintf`. A read operation with `fgetl`, `fgets`, or `fscanf` completes when the `Terminator` value is read. The terminator is ignored for binary operations.

You can also use the terminator to generate a bytes-available event when the `BytesAvailableFcnMode` is set to `terminator`.

### Characteristics

Read only	Never
Data type	String

### Values

An integer value ranging from 0 to 127, or the equivalent ASCII character. `CR/LF` and `LF/CR` are also accepted values. You specify different read and write terminators as a 1-by-2 cell array.

## See Also

### Functions

fgetl, fgets, fprintf, fscanf

### Properties

BytesAvailableFcnMode

## Timeout

Waiting time to complete a read or write operation

## Description

You configure `Timeout` to be the maximum time (in seconds) to wait to complete a read or write operation.

If a time-out occurs, the read or write operation aborts. Additionally, if a time-out occurs during an asynchronous read or write operation, then:

- An error event is generated.
- The callback function specified for `ErrorFcn` is executed.

## Characteristics

Read only	Never
Data type	Double

## Values

The default value is 10 seconds.

## See Also

### Properties

`ErrorFcn`

## TimerFcn

Specify the callback function to execute when a predefined period of time passes.

### Description

You configure `TimerFcn` to execute a callback function when a timer event occurs. A timer event occurs when the time specified by the `TimerPeriod` property passes. Time is measured relative to when the serial port object is connected to the device with `fopen`.

---

**Note:** A timer event can be generated at any time during the serial port session.

---

If the `RecordStatus` property value is `on`, and a timer event occurs, the record file records this information:

- The event type as `Timer`
- The time the event occurred using the format `day-month-year hour:minute:second:millisecond`

Some timer events might not be processed if your system is significantly slowed or if the `TimerPeriod` value is too small.

To learn how to create a callback function, see “Create and Execute Callback Functions” on page 17-51.

### Characteristics

Read only	Never
Data type	Callback function

### Values

The default value is an empty string.

## **See Also**

### **Functions**

fopen, record

### **Properties**

RecordStatus, TimerPeriod



# TimerPeriod

Period of time between timer events

## Description

TimerPeriod specifies the time, in seconds, that must pass before the callback function specified for `TimerFcn` is called. Time is measured relative to when the serial port object is connected to the device with `fopen`.

Some timer events might not be processed if your system is significantly slowed or if the TimerPeriod value is too small.

## Characteristics

Read only	Never
Data type	Callback function

## Values

The default value is 1 second. The minimum value is 0.01 second.

## See Also

### Functions

`fopen`

### Properties

`TimerFcn`

## TransferStatus

Indicate if an asynchronous read or write operation is in progress

### Description

`TransferStatus` can be `idle`, `read`, `write`, or `read&write`. If `TransferStatus` is `idle`, no asynchronous read or write operations are in progress. If `TransferStatus` is `read`, an asynchronous read operation is in progress. If `TransferStatus` is `write`, an asynchronous write operation is in progress. If `TransferStatus` is `read&write`, both an asynchronous read and an asynchronous write operation are in progress.

You can write data asynchronously using the `fprintf` or `fwrite` functions. You can read data asynchronously using the `readasync` function, or by configuring the `ReadAsyncMode` property to `continuous`. While `readasync` is executing, `TransferStatus` might indicate that data is being read even though data is not filling the input buffer. If `ReadAsyncMode` is `continuous`, `TransferStatus` indicates that data is being read only when data is actually filling the input buffer.

You can execute an asynchronous read and an asynchronous write operation simultaneously because serial ports have separate read and write pins. For more information about synchronous and asynchronous read and write operations, see “Write and Read Data” on page 17-28.

### Characteristics

Read only	Always
Data type	String

### Values

<code>{idle}</code>	No asynchronous operations are in progress.
<code>read</code>	An asynchronous read operation is in progress.

write	An asynchronous write operation is in progress.
read&write	Asynchronous read and write operations are in progress.

## See Also

### Functions

fprintf, fwrite, readasync

### Properties

ReadAsyncMode

## Type

Object type

## Description

Type indicates the type of the object. Type is automatically defined after the serial port object is created with the `serial` function. The Type value is always `serial`.

## Characteristics

Read only	Always
Data type	String

## Values

Type is always `serial`. This value is automatically defined when the serial port object is created.

## Example

Suppose you create a serial port object associated with the serial port COM1.

```
s = serial('COM1');
```

The value of the Type property is `serial`, which is the object class.

```
s.Type  
ans =  
serial
```

You can also display the object class with the `whos` command.

```
Name      Size      Bytes  Class
```

s 1x1 644 serial object

Grand total is 18 elements using 644 bytes

## See Also

### Functions

serial

## UserData

Data you want to associate with a serial port object

## Description

You configure `UserData` to store data that you want to associate with a serial port object. The object does not use this data directly, but you can access it using the `get` function or the dot notation.

## Characteristics

Read only	Never
Data type	Any type

## Values

The default value is an empty vector.

## Example

Suppose you create the serial port object associated with the serial port COM1.

```
s = serial('COM1');
```

You can associate data with `s` by storing it in `UserData`.

```
coeff.a = 1.0;  
coeff.b = -1.25;  
s.UserData = coeff;
```

# ValuesReceived

Total number of values read from the device

## Description

ValuesReceived indicates the total number of values read from the device. The value is updated after each successful read operation, and is set to 0 after the `fopen` function is issued. If the terminator is read from the device, then this value is reflected by ValuesReceived.

If you are reading data asynchronously, use the `BytesAvailable` property to return the number of bytes currently available in the input buffer.

When performing a read operation, the received data is represented by values rather than bytes. A value consists of one or more bytes. For example, one `uint32` value consists of four bytes. For more information about bytes and values, see “Bytes Versus Values” on page 17-10.

## Characteristics

Read only	Always
Data type	Double

## Values

The default value is 0.

## Example

Suppose you create a serial port object associated with the serial port COM1.

```
s = serial('COM1');  
fopen(s)
```

If you write the `RS232?` command, and read back the response using `fscanf`, `ValuesReceived` is 17 because the instrument is configured to send the LF terminator.

```
fprintf(s, 'RS232?')
out = fscanf(s)
out =
9600;0;0;NONE;LF
s.ValuesReceived
ans =
    17
```

## See Also

### Functions

`fopen`

### Properties

`BytesAvailable`



# ValuesSent

Total number of values written to the device

## Description

ValuesSent indicates the total number of values written to the device. The value is updated after each successful write operation, and is set to 0 after the `fopen` function is issued. If you are writing the terminator, ValuesSent reflects this value.

If you are writing data asynchronously, use the BytesToOutput property to return the number of bytes currently in the output buffer.

When performing a write operation, the transmitted data is represented by values rather than bytes. A value consists of one or more bytes. For example, one `uint32` value consists of four bytes. For more information about bytes and values, see “Bytes Versus Values” on page 17-10.

## Characteristics

Read only	Always
Data type	Double

## Values

The default value is 0.

## Example

Suppose you create a serial port object associated with the serial port COM1.

```
s = serial('COM1');  
fopen(s)
```

If you write the `*IDN?` command using the `fprintf` function, `ValuesSent` is `6` because the default data format is `%s\n`, and the terminator was written.

```
fprintf(s, '*IDN?')
s.ValuesSent
ans =
     6
```

## See Also

### Functions

`fopen`

### Properties

`BytesToOutput`

# Hardware Support

---

- “Support Package Installation” on page 18-2
- “Support Package Installer Help” on page 18-3
- “MATLAB Supported Hardware” on page 18-17
- “Change Your Support Package Directory” on page 18-18

## Support Package Installation

<b>In this section...</b>
“What Is a Support Package?” on page 18-2
“Install Support Packages” on page 18-2

### What Is a Support Package?

A *support package* is an add-on that enables you to use a MathWorks product with specific third-party hardware and software.

For example, support packages available for use with MATLAB include:

- Arduino® Hardware
- LEGO® MINDSTORMS® EV3 Hardware
- Raspberry Pi™ Hardware
- USB Webcam

For a complete list of available support packages, see Hardware Support.

### Install Support Packages

You install support packages using the MATLAB **Add-Ons** menu. You can also use **Add-Ons** to update installed support package software or update the firmware on third-party hardware.

To install support packages, on the MATLAB **Home** tab, in the **Environment** section, click **Add-Ons > Get Hardware Support Packages**.

### More About

- “Get Add-Ons”
- “Manage Your Add-Ons”

### External Websites

- Hardware Support Catalog

## Support Package Installer Help

### In this section...

“About Support Package Installer” on page 18-3

“Select an Action” on page 18-4

“Select Support Package to Install or Select Support Package to Download” on page 18-5

“Log In to MathWorks Account” on page 18-8

“The MathWorks, Inc. Software License Agreement” on page 18-10

“Third-Party Software Licenses” on page 18-11

“Confirm Installation, Confirm Download, Confirm Uninstall” on page 18-12

“Install or Update Complete, Download Complete, Uninstall Complete” on page 18-13

“Set Up Support Package” on page 18-14

“Support Package Setup Complete” on page 18-16

“Special Instructions” on page 18-16


### About Support Package Installer

Use Support Package Installer to add support for third-party products to your MathWorks software. When you complete the installation process, you can use the MathWorks software with those third-party products.

To start Support Package Installer, enter `supportPackageInstaller` in a MATLAB Command Window.

The following topics provide help for each screen in the Support Package Installer.


## Select an Action



You can use **Select an action** to choose the action Support Package Installer performs:

- **Install from Internet:** Download a support package from the Internet and install it on the host computer.
- **Download from Internet:** Download a support package from the Internet without installing it.
- **Install from folder:** Install a previously downloaded support package.
- **Uninstall:** Uninstall a specific support package.

## Select Support Package to Install or Select Support Package to Download



Support Package Installer installs those support package or packages that are currently visible in the right pane. In other words, it only installs support for one type of hardware at a time.

Use **Support for** to choose a specific group of support packages. Support Package Installer can only install or act upon one particular group of support packages at a time.

You can use **Show** to filter the support packages Support Package Installer displays:

- All displays support packages for all base products and host computer platforms.

- **Installable** displays support packages that you can install with the product licenses and platform on your host computer.
- **Installed** displays support packages that are installed on your host computer.
- **Updatable** displays installed support packages for which updates are available.

To install support packages in multiple groups, rerun Support Package Installer for each group.

Use **Support packages** to choose and review the status of specific support packages. Support Package Installer organizes the following support package information in columns:

- **Action** displays the action Support Package Installer can perform upon a support package. Select or clear the check box in to enable or disable Support Package Installer from performing that action: **Install, Reinstall, Update, None**.
- **Installed Version** displays the version of the installed support package. This entry is blank if the support package is not installed. If Latest Version and Installed Version are different, you can update the support package.
- **Latest Version** displays the version of the support package that is available for download. If Latest Version and Installed Version are different, you can update the support package. If your computer does not have access to the Internet, this value is empty.
- **Description** links to a web page where you can look or search for more information about the support package.
- **Required Base Product** displays the base product that is required in order to install the support package. If the base product is not licensed and installed, the support package is not downloadable or installable.
- **Supported Host Platforms** displays the host computer platforms required to install the support package. If the host computer is not one of the supported platforms, you cannot download or install the support package. **Win32** and **Win64** represent the 32- and 64-bit versions of Microsoft Windows. **Linux64** represents the 64-bit version of Linux. **Mac64** represents the 64-bit version of the Apple Mac platform.

The **Installation folder** parameter displays the path where Support Package Installer installs the support package. You must have write privileges for this folder. The installation folder has a set default, however you can set a custom directory to install your support package to a different location. For more info, see “Change Your Support Package Directory” on page 18-18



If you choose the **Download from Internet** option, Support Package Installer displays the **Download folder** parameter instead of the **Installation folder** parameter.

**Download folder** displays the path where Support Package Installer creates support package folders. You must have write privileges for this path. You can enter a new path directly, or use the **Browse** button to select one. By default, the **Download folder** is named `downloads`. After installing support packages, the **Download folder** contains subfolders for each support package.


The **Find more supported hardware** link opens a browser and displays the Hardware Support topic on the MathWorks website.

---

**Note:** Opening a support package installation file opens the **Select a Support Package to Install or Download** screen with a support package preselected. These files are available from MATLAB Central File Exchange, and have the file name extension:  
`*.mlpkginstall`


---

## Log In to MathWorks Account



Click **Log In**. In the **MathWorks Account Log In** dialog box, enter your MathWorks.com account email address and password. For more information, see <http://www.mathworks.com/support/solutions/en/data/1-172ME/index.html?solution=1-172ME>.

If you do not have an account, click [here](#) to create one.



MathWorks Account Log In

Don't have an account? [Create an account](#)


Email address:

Password:

Keep me logged on


[Forgot your password?](#)

## The MathWorks, Inc. Software License Agreement



Review the text of the license agreement. If you agree, select the **I accept** check box, and then click **Next**.


## Third-Party Software Licenses



Support packages that download third-party software as part of the installation process display this screen. Review the information and any license agreements.

To proceed, click **Install**. Otherwise, click **Back** or **Cancel**.

## Confirm Installation, Confirm Download, Confirm Uninstall



This screen confirms the name of the support package you have chosen. To continue, click **Install**, **Download**, or **Uninstall**.


Support Package Installer displays a progress bar while it performs the specified action.

---

**Note:** If Support Package Installer instructs you to delete files, close the MATLAB software before removing the files. Then, restart MATLAB software and run Support Package Installer to complete the process.

---

## Install or Update Complete, Download Complete, Uninstall Complete



Support Package Installer has finished installing or uninstalling the support package.

Some support packages require additional actions before you can use the support package:


- Replace or update the firmware on the target hardware.
- Install and validate required third-party software.

To perform these actions, click **Continue**. Otherwise, click **Finish**.

This screen displays the path of the support package folder within the **Download folder**. If you use the **Install from Folder** option in the future, you will specify the location of this support package folder.

If there are no additional actions, and the support package contains featured examples, Support Package Installer gives you the option to open the featured examples. These examples show you how to use the capabilities provided by the support package.

## Set Up Support Package





This screen is only shown for support packages that provide additional post-installation steps. Use the **Support package for** parameter to identify the third-party hardware or software to set up. Then, click **Next**.

The subsequent screens guide you through the process of:


- Replacing or updating the firmware on the target hardware.
- Installing and validating required third-party software.

---

**Note:** To return to this screen without repeating preceding screens, enter `targetupdater` in a MATLAB Command Window.

---

## Support Package Setup Complete



You have completed the set up process.

If you leave the **Show support package examples** check box selected and click **Finish**, Support Package Installer displays support package examples in a new window.

### Special Instructions

This screen is unique to the support package you are installing. Carefully read and follow the instructions provided by the screen.

## MATLAB Supported Hardware

For a complete list of support packages, see the Hardware Support Catalog.

In addition to these packages, MATLAB includes built-in support for:

- “Audio Recording and Playback”
- “Serial Port Devices”

## Change Your Support Package Directory

When installing support packages, the root directory is set to a default location for your specific system.

- For Windows, the default root directory is :

```
'C:\MATLAB\SupportPackage\'
```

where `<release>` is your specific MATLAB release.

If the default directory already exists and is not empty, the root directory becomes `'C:\MATLAB\SupportPackages\_1'`.

- For Unix, the default root directory is:

```
'/home/user/Documents/MATLAB/SupportPackages/'
```

where `<release>` is your specific MATLAB release.

If the computed default directory already exists and is not empty, it becomes `'/home/user/Documents/MATLAB/SupportPackages\_1'`.

You can change the location if your application requires a custom directory for installation. You must have administration privileges and be able to write to this custom folder. In order to set the support package root and verify the change, follow this example:

---

**Note:** You must have administration privileges for the custom folder you specify.

---

```
matlabshared.supportpkg.setSupportPackageRoot('C:\MATLAB\CustomSupportPackageRoot')
matlabshared.supportpkg.getSupportPackageRoot()

ans =

C:\MATLAB\CustomSupportPackageRoot
```

When setting the support package root, `savepath` is called to add the location to the MATLAB search path. To ensure the path is loaded correctly, start MATLAB, run the `setSupportPackageRoot` function, and then restart MATLAB.

---

**Note:** It is not recommended you use multiple different directories to install separate support packages. Only the support packages installed on the current directory can be used.

---

