

Mapping Toolbox™

Reference



MATLAB®

R2018a

 MathWorks®

How to Contact MathWorks



Latest news: www.mathworks.com
Sales and services: www.mathworks.com/sales_and_services
User community: www.mathworks.com/matlabcentral
Technical support: www.mathworks.com/support/contact_us



Phone: 508-647-7000



The MathWorks, Inc.
3 Apple Hill Drive
Natick, MA 01760-2098

Mapping Toolbox™ Reference

© COPYRIGHT 1997–2018 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See www.mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

Patents

MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

Revision History

| | | |
|----------------|------------------|--|
| May 1997 | First printing | New for Version 1.0 |
| October 1998 | Second printing | Version 1.1 |
| November 2000 | Third printing | Version 1.2 (Release 12) |
| July 2002 | Online only | Revised for Version 1.3 (Release 13) |
| September 2003 | Online only | Revised for Version 1.3.1 (Release 13SP1) |
| January 2004 | Online only | Revised for Version 2.0 (Release 13SP1+) |
| April 2004 | Online only | Revised for Version 2.0.1 (Release 13SP1+) |
| June 2004 | Fourth printing | Revised for Version 2.0.2 (Release 14) |
| October 2004 | Online only | Revised for Version 2.0.3 (Release 14SP1) |
| March 2005 | Fifth printing | Revised for Version 2.1 (Release 14SP2) |
| August 2005 | Sixth printing | Minor revision for Version 2.1 |
| September 2005 | Online only | Revised for Version 2.2 (Release 14SP3) |
| March 2006 | Online only | Revised for Version 2.3 (Release 2006a) |
| September 2006 | Seventh printing | Revised for Version 2.4 (Release 2006b) |
| March 2007 | Online only | Revised for Version 2.5 (Release 2007a) |
| September 2007 | Eighth printing | Revised for Version 2.6 (Release 2007b) |
| March 2008 | Online only | Revised for Version 2.7 (Release 2008a) |
| October 2008 | Online only | Revised for Version 2.7.1 (Release 2008b) |
| March 2009 | Online only | Revised for Version 2.7.2 (Release 2009a) |
| September 2009 | Online only | Revised for Version 3.0 (Release 2009b) |
| March 2010 | Online only | Revised for Version 3.1 (Release 2010a) |
| September 2010 | Online only | Revised for Version 3.2 (Release 2010b) |
| April 2011 | Online only | Revised for Version 3.3 (Release 2011a) |
| September 2011 | Online only | Revised for Version 3.4 (Release 2011b) |
| March 2012 | Online only | Revised for Version 3.5 (Release 2012a) |
| September 2012 | Online only | Revised for Version 3.6 (Release 2012b) |
| March 2013 | Online only | Revised for Version 3.7 (Release 2013a) |
| September 2013 | Online only | Revised for Version 4.0 (Release 2013b) |
| March 2014 | Online only | Revised for Version 4.0.1 (Release 2014a) |
| October 2014 | Online only | Revised for Version 4.0.2 (Release 2014b) |
| March 2015 | Online only | Revised for Version 4.1 (Release 2015a) |
| September 2015 | Online only | Revised for Version 4.2 (Release 2015b) |
| March 2016 | Online only | Revised for Version 4.3 (Release 2016a) |
| September 2016 | Online only | Revised for Version 4.4 (Release 2016b) |
| March 2017 | Online only | Revised for Version 4.5 (Release 2017a) |
| September 2017 | Online only | Revised for Version 4.5.1 (Release 2017b) |
| March 2018 | Online only | Revised for Version 4.6 (Release 2018a) |

| | |
|----------|--------------------------------------|
| 1 | Functions – Alphabetical List |
|----------|--------------------------------------|

Functions — Alphabetical List

Map Viewer

View and explore data in map coordinates

Description

The Map Viewer app enables you to view geospatial data in map (x-y) coordinates. The Map Viewer works with vector, image, and raster data grids in a map coordinate system. You can pan and zoom on the map, specify the map scale of your screen display, and control the order, visibility, and symbolization of map layers. In addition, you can add annotations to your map and click to learn more about individual vector features.

Open the Map Viewer App

- MATLAB® Toolstrip: Open the Apps tab, under **Image Processing and Computer Vision**, click the app icon.
- MATLAB command prompt: Enter `mapview`.

Examples

- “Tour Boston with the Map Viewer App”

See Also

Functions

`mapshow`

Topics

“Tour Boston with the Map Viewer App”

Introduced before R2006a

aer2ecef

Local spherical AER to geocentric ECEF

Syntax

```
[X,Y,Z] = aer2ecef(az,elev,slantRange,lat0,lon0,h0,spheroid)  
[ ___ ] = aer2ecef( ___,angleUnit)
```

Description

[X,Y,Z] = aer2ecef(az,elev,slantRange,lat0,lon0,h0,spheroid) returns Earth-Centered Earth-Fixed (ECEF) spheroid-centric Cartesian coordinates corresponding to coordinates az, elev, slantRange in a local spherical system having the same origin. Any of the first six numerical input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

[___] = aer2ecef(___,angleUnit) adds angleUnit which specifies the units of inputs az, elev, lat0, and lon0.

Input Arguments

az — Azimuth angles

scalar value | vector | matrix | N-D array

Azimuth angles in the local spherical system, specified as a scalar, vector, matrix, or N-D array. Azimuths are measured clockwise from north. Values must be in units that match the input argument angleUnit, if supplied, and in degrees, otherwise.

Data Types: single | double

elev — Elevation angles

scalar value | vector | matrix | N-D array

Elevation angles in the local spherical system, specified as a scalar, vector, matrix, or N-D array. Elevations are with respect to a plane perpendicular to the spheroid surface

normal. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

s`slantRange` — Distances from local origin

scalar value | vector | matrix | N-D array

Distances from origin in the local spherical system, returned as a scalar, vector, matrix, or N-D array. The straight-line, 3-D Cartesian distance is used. Units are determined by the `LengthUnit` property of the `spheroid` input.

Data Types: `single` | `double`

l`lat0` — Geodetic latitude of local origin

scalar value | vector | matrix | N-D array

Geodetic latitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lat0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

l`lon0` — Longitude of local origin

scalar value | vector | matrix | N-D array

Longitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lon0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

h`h0` — Ellipsoidal height of local origin

scalar value | vector | matrix | N-D array

Ellipsoidal height of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `h0` is scalar, but it need not be. (It may refer to a moving platform, for example). Units are determined by the `LengthUnit` property of the `spheroid` input.

Data Types: `single` | `double`

spheroid — Reference spheroid

`referenceEllipsoid` | `oblateSpheroid` | `referenceSphere`

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. To create a spheroid object, use the creation function specific to the object, or the `wgs84Ellipsoid` function.

Example: `spheroid = referenceEllipsoid('GRS 80');`

angleUnit — Units of angles

`'degrees'` (default) | `'radians'`

Units of angles, specified as `'degrees'` (default), or `'radians'`.

Data Types: `char` | `string`

Output Arguments

X — ECEF x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid object.

Y — ECEF y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid object.

Z — ECEF z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid object.

See Also

aer2geodetic | ecef2aer | enu2ecef | ned2ecef

Introduced in R2012b

aer2enu

Local spherical AER to local Cartesian ENU

Syntax

```
[xEast,yNorth,zUp] = aer2enu(az,elev,slantRange)  
[ ___ ] = aer2enu( ___ ,angleUnit)
```

Description

[xEast,yNorth,zUp] = aer2enu(az,elev,slantRange) returns coordinates in a local east-north-up (ENU) Cartesian system corresponding to coordinates az, elev, slantRange in a local spherical system having the same origin. Any of the three numerical input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

[___] = aer2enu(___ ,angleUnit) adds angleUnit which specifies the units of inputs az and elev.

Input Arguments

az — Azimuth angles

scalar value | vector | matrix | N-D array

Azimuth angles in the local spherical system, specified as a scalar, vector, matrix, or N-D array. Azimuths are measured clockwise from north. Values must be in units that match the input argument angleUnit, if supplied, and in degrees, otherwise.

Data Types: single | double

elev — Elevation angles

scalar value | vector | matrix | N-D array

Elevation angles in the local spherical system, specified as a scalar, vector, matrix, or N-D array. Elevations are with respect to a plane perpendicular to the spheroid surface

normal. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: `char` | `string`

slantRange — Distances from local origin

scalar value | vector | matrix | N-D array

Distances from origin in the local spherical system, specified as a scalar, vector, matrix, or N-D array. The straight-line, 3-D Cartesian distance is used.

Data Types: `single` | `double`

Output Arguments

xEast — Local ENU x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the local ENU system, returned as a scalar value, vector, matrix, or N-D array.

yNorth — Local ENU y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the local ENU system, returned as a scalar value, vector, matrix, or N-D array.

zUp — Local ENU z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the local ENU system, returned as a scalar value, vector, matrix, or N-D array.

See Also

aer2ned | enu2aer

Introduced in R2012b

aer2geodetic

Local spherical AER to geodetic

Syntax

```
[lat,lon,h] = aer2geodetic(az,elev,slantRange,lat0,lon0,h0,spheroid)  
[ ___ ] = aer2geodetic( ___,angleUnit)
```

Description

`[lat,lon,h] = aer2geodetic(az,elev,slantRange,lat0,lon0,h0,spheroid)` returns geodetic coordinates corresponding to coordinates `az`, `elev`, `slantRange` in a local spherical system. Any of the first six numeric input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

`[___] = aer2geodetic(___,angleUnit)` adds `angleUnit` which specifies the units of inputs `az`, `elev`, `lat0`, `lon0`, and outputs `lat`, `lon`.

Examples

Zermatt to the Matterhorn

Compute the latitude, longitude and orthometric height of the summit of the Matterhorn (Monte Cervino) from its azimuth, elevation and (slant) range relative to Zermatt, Switzerland. All distances and lengths are in meters.

Origin (reference point): Zermatt.

```
fmt = get(0,'Format');  
format short g  
  
lat0 = dm2degrees([46 1])    % convert degree-minutes to degrees  
lon0 = dm2degrees([ 7 45])  
hOrthometric0 = 1620;
```

```
hGeoid = 53;  
h0 = hOrthometric0 + hGeoid
```

```
lat0 =  
    46.017
```

```
lon0 =  
    7.75
```

```
h0 =  
    1673
```

Azimuth, elevation, and slant range to Matterhorn summit.

```
az = 237.8;  
elev = 18.755;  
slantRange = 8871.7;
```

Latitude, longitude, and ellipsoidal height of summit.

```
[lat, lon, hEllipsoidal] = aer2geodetic( ...  
    az, elev, slantRange, lat0, lon0, h0, wgs84Ellipsoid)
```

```
lat =  
    45.976
```

```
lon =  
    7.6583
```

```
hEllipsoidal =  
    4531
```

Orthometric height of summit.

```
hGeoid = 53;
hOrthometric = hEllipsoidal - hGeoid
format(fmt)

hOrthometric =

    4478
```

Input Arguments

az — Azimuth angles

scalar value | vector | matrix | N-D array

Azimuth angles in the local spherical system, specified as a scalar, vector, matrix, or N-D array. Azimuths are measured clockwise from north. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

elev — Elevation angles

scalar value | vector | matrix | N-D array

Elevation angles in the local spherical system, specified as a scalar, vector, matrix, or N-D array. Elevations are with respect to a plane perpendicular to the spheroid surface normal. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

sLantRange — Distances from local origin

scalar value | vector | matrix | N-D array

Distances from origin in the local spherical system, returned as a scalar, vector, matrix, or N-D array. The straight-line, 3-D Cartesian distance is used. Units are determined by the `LengthUnit` property of the spheroid input.

Data Types: `single` | `double`

lat0 — Geodetic latitude of local origin

scalar value | vector | matrix | N-D array

Geodetic latitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of

`lat0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon0 — Longitude of local origin

scalar value | vector | matrix | N-D array

Longitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lon0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

h0 — Ellipsoidal height of local origin

scalar value | vector | matrix | N-D array

Ellipsoidal height of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `h0` is scalar, but it need not be. (It may refer to a moving platform, for example). Units are determined by the `LengthUnit` property of the spheroid input.

Data Types: `single` | `double`

spheroid — Reference spheroid

`referenceEllipsoid` | `oblateSpheroid` | `referenceSphere`

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. To create a spheroid object, use the creation function specific to the object, or the `wgs84Ellipsoid` function.

Example: `spheroid = referenceEllipsoid('GRS 80');`

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: `char` | `string`

Output Arguments

lat — Geodetic latitudes

scalar value | vector | matrix | N-D array

Geodetic latitudes of one or more points, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the input argument `angleUnit`, if supplied; values are in degrees, otherwise. When in degrees, they lie in the closed interval [-90 90].

lon — Longitudes

scalar value | vector | matrix | N-D array

Longitudes of one or more points, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the input argument `angleUnit`, if supplied; values are in degrees, otherwise. When in degrees, they lie in the interval [-180 180].

h — Ellipsoidal heights

scalar value | vector | matrix | N-D array

Ellipsoidal heights of one or more points, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the `spheroid` object

See Also

`aer2ecef` | `enu2geodetic` | `geodetic2aer` | `ned2geodetic`

Introduced in R2012b

aer2ned

Local spherical AER to local Cartesian NED

Syntax

```
[xNorth,yEast,zDown] = aer2ned(az,elev,slantRange)
[ ___ ] = aer2ned( ___ ,angleUnit)
```

Description

[xNorth,yEast,zDown] = aer2ned(az,elev,slantRange) returns coordinates in a local north—east—down (NED) Cartesian system corresponding to coordinates az, elev, slantRange in a local spherical system having the same origin. Any of the three numerical input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

[___] = aer2ned(___ ,angleUnit) adds angleUnit which specifies the units of inputs az and elev..

Input Arguments

az — Azimuth angles

scalar value | vector | matrix | N-D array

Azimuth angles in the local spherical system, specified as a scalar, vector, matrix, or N-D array. Azimuths are measured clockwise from north. Values must be in units that match the input argument angleUnit, if supplied, and in degrees, otherwise.

Data Types: single | double

elev — Elevation angles

scalar value | vector | matrix | N-D array

Elevation angles in the local spherical system, specified as a scalar, vector, matrix, or N-D array. Elevations are with respect to a plane perpendicular to the spheroid surface

normal. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

sLantRange — Distances from local origin

scalar value | vector | matrix | N-D array

Distances from origin in the local spherical system, returned as a scalar, vector, matrix, or N-D array. The straight-line, 3-D Cartesian distance is used. Units are determined by the `LengthUnit` property of the spheroid input.

Data Types: `single` | `double`

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: `char` | `string`

Output Arguments

xNorth — Local NED x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the local NED system, returned as a scalar value, vector, matrix, or N-D array.

yEast — Local NED y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the local NED system, returned as a scalar value, vector, matrix, or N-D array.

zDown — Local NED z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the local NED system, returned as a scalar value, vector, matrix, or N-D array.

See Also

aer2enu | ned2aer

Introduced in R2012b

almanac

Parameters for Earth, planets, Sun, and Moon

Note `almanac` is not recommended. Use `earthRadius`, `referenceEllipsoid`, `referenceSphere`, or `wgs84Ellipsoid` instead.

Syntax

```
almanac
almanac(body)
data = almanac(body,parameter)
data = almanac(body,parameter,units)
data = almanac(parameter,units,referencebody)
```

Description

`almanac` displays the names of the celestial objects available in the almanac.

`almanac(body)` lists the options, or parameters, available for any of the following celestial bodies:

```
'earth'      'pluto'
'jupiter'    'saturn'
'mars'       'sun'
'mercury'    'uranus'
'moon'       'venus'
'neptune'
```

`data = almanac(body,parameter)` returns the value of the requested parameter for the celestial body specified by *body*.

Valid parameter values are `'radius'` for the planetary radius, `'ellipsoid'` or `'geoid'` for the two-element ellipsoid vector, `'surfarea'` for the surface area, and `'volume'` for the planetary volume.

For the Earth, parameter can also be any of the following valid predefined ellipsoid values. In this case, the two-element ellipsoid vector for that ellipsoid model is returned. Valid ellipsoid definitions for the Earth are:

| | |
|-----------------|---|
| 'everest' | 1830 Everest ellipsoid |
| 'bessel' | 1841 Bessel ellipsoid |
| 'airy' | 1830 Airy ellipsoid |
| 'clarke66' | 1866 Clarke ellipsoid |
| 'clarke80' | 1880 Clarke ellipsoid |
| 'international' | 1924 International ellipsoid |
| 'krasovsky' | 1940 Krasovsky ellipsoid |
| 'wgs60' | 1960 World Geodetic System ellipsoid |
| 'iau65' | 1965 International Astronomical Union ellipsoid |
| 'wgs66' | 1966 World Geodetic System ellipsoid |
| 'iau68' | 1968 International Astronomical Union ellipsoid |
| 'wgs72' | 1972 World Geodetic System ellipsoid |
| 'grs80' | 1980 Geodetic Reference System ellipsoid |
| 'wgs84' | 1984 World Geodetic System ellipsoid |

For the Earth, the parameter values 'ellipsoid' and 'geoid' are equivalent to 'grs80'.

`data = almanac(body,parameter,units)` specifies the units to be used for the output measurement, where `units` is any valid distance units . Note that these are linear units, but the result for surface area is in square units, and for volume is in cubic units. The default units are 'kilometers'.

`data = almanac(parameter,units,referencebody)` specifies the source of the information. This sets the assumptions about the shape of the celestial body used in the calculation of volumes and surface areas. A `referencebody` of 'actual' returns a tabulated value rather than one dependent upon a ellipsoid model assumption. Other possible `referencebody` s are 'sphere' for a spherical assumption and 'ellipsoid' for the default ellipsoid model. The default reference body is 'sphere'.

For the Earth, any of the preceding predefined ellipsoid definitions can also be entered as a reference body.

For Mercury, Pluto, Venus, the Sun, and the Moon, the eccentricity of the ellipsoid model is zero, that is, the 'ellipsoid' reference body is actually a sphere.

Tips

Take care when using angular arc length units for distance measurements. All planets have a radius of 1 radian, for example, and an area unit of *square degrees* indicates unit squares, 1 degree of arc length on a side, not 1-degree-by-1-degree quadrangles.

See Also

`distance` | `earthRadius` | `referenceEllipsoid` | `referenceSphere` | `wgs84Ellipsoid`

Introduced before R2006a

angl2str

Convert angles to character array

Syntax

```
str = angl2str(angle)
str = angl2str(angle,signcode)
str = angl2str(angle,signcode,units)
str = angl2str(angle,signcode,units,n)
```

Description

`str = angl2str(angle)` converts a numerical vector of angles in degrees to a character array. The purpose of this function is to make angular-valued variables into character vectors suitable for map display.

`str = angl2str(angle,signcode)` specifies the method for indicating that a given angle is positive or negative, where `signcode` is one of the following:

| | |
|--------|---|
| 'ew' | east/west notation; trailing 'e' (positive longitudes) or 'w' (negative longitudes) |
| 'ns' | north/south notation; trailing 'n' (positive latitudes) or 's' (negative latitudes) |
| 'pm' | plus/minus notation; leading '+' (positive angles) or '-' (negative angles) |
| 'none' | blank/minus notation; leading '-' for negative angles or sign omitted for positive angles (the default value) |

`str = angl2str(angle,signcode,units)` specifies the units and the output format of the returned angle, using the following values:

| Units | Units of Angle | Output Format |
|--------------|----------------|---------------------------|
| 'degrees' | degrees | decimal degrees |
| 'degrees2dm' | degrees | degrees + decimal minutes |

| Units | Units of Angle | Output Format |
|---------------|----------------|-------------------------------------|
| 'degrees2dms' | degrees | degrees + minutes + decimal seconds |
| 'radians' | radians | decimal radians |

`str = angl2str(angle, signcode, units, n)` uses the integer `n` to control the number of significant digits provided in the output. `n` is the power of 10 representing the last place of significance in the number of degrees, minutes, seconds, or radians -- for units of 'degrees', 'degrees2dm', 'degrees2dms', and 'radians', respectively. For example, if `n = -2` (the default), `angl2str` rounds to the nearest hundredth. If `n = -0`, `angl2str` rounds to the nearest integer. And if `n = 1`, `angl2str` rounds to the tens place, although positive values of `n` are of little practical use. Note that this sign convention for `n` is opposite to the one used by the MATLAB `round` function.

Examples

Convert Numeric Angles to String Matrix

Create a series of values for angles.

```
a = -3:1.5:3;
```


Convert the numeric values in DMS units, using the north-south format.

```
str = angl2str(a, 'ns', 'degrees2dms', -3)
```

```
str = 5x25 char array
    ' 3^{\circ} 00' 00.000" S '
    ' 1^{\circ} 30' 00.000" S '
    ' 0^{\circ} 00' 00.000"   '
    ' 1^{\circ} 30' 00.000" N '
    ' 3^{\circ} 00' 00.000" N '
```

These LaTeX strings are displayed (using the `text` function) as follows:

```
x = [.1 .1 .1 .1 .1];
y = [.1 .2 .3 .4 .5];
text(x,y,str)
```

See Also

`dist2str` | `str2angle`

Introduced before R2006a

angledim

Convert angles units

Note The `angledim` function has been replaced by four, more specific, functions: `fromRadians`, `fromDegrees`, `toRadians`, and `toDegrees`. However, `angledim` will be maintained for backward compatibility. The functions `deg2rad`, `rad2deg`, and `unitsratio` provide additional alternatives.

Syntax

```
angleOut = angledim(angleIn, from, to)
```

Description

`angleOut = angledim(angleIn, from, to)` returns the value of the input angle `angleIn`, which is in units specified by *from*, in the desired units given by *to*. Angle units are 'degrees' for “decimal” degrees or 'radians' for radians.

Examples

Convert from degrees to radians:

```
angledim(23.45134, 'degrees', 'radians')
```

```
ans =  
    0.4093
```

See Also

`deg2rad` | `degrees2dms` | `fromDegrees` | `fromRadians` | `rad2deg` | `toDegrees` | `toRadians` | `unitsratio`

Introduced before R2006a

antipode

Point on opposite side of globe

Syntax

```
[newlat,newlon] = antipode(lat,lon)
[newlat,newlon] = antipode(lat,lon,angleunits)
```

Description

`[newlat,newlon] = antipode(lat,lon)` returns the geographic coordinates of the points exactly opposite on the globe from the input points given by `lat` and `lon`. All angles are in degrees.

`[newlat,newlon] = antipode(lat,lon,angleunits)` where `angleunits` specifies the input and output units as either 'degrees' or 'radians'. It can be abbreviated and is case-insensitive.

Examples

Find Antipode of Given Point

Given a point (43°N, 15°E), find its antipode:

```
[newlat,newlong] = antipode(43,15)
newlat =
    -43
newlong =
   -165
```

or (43°S, 165°W).

Find Antipode of North and South Poles

Perhaps the most obvious antipodal points are the North and South Poles. The function `antipode` demonstrates this:

```
[newlat,newlong] = antipode(90,0,'degrees')
newlat =
    -90
newlong =
    180
```

Note that in this case longitudes are irrelevant because all meridians converge at the poles.

Find Antipode of MathWorks Headquarters

This example shows how to find the antipode of the location of the MathWorks corporate headquarters in Natick, Massachusetts. The example maps the headquarters location and its antipode in an orthographic projection.

Specify latitude and longitude as degree-minutes-seconds and then convert to decimal degrees.

```
mwlats = dms2degrees([ 42 18 2.5])
mwlats = 42.3007
mwlon = dms2degrees([-71 21 7.9])
mwlon = -71.3522
```

Find the antipode.

```
[amwlat amwlon] = antipode(mwlat,mwlon)
amwlat = -42.3007
amwlon = 108.6478
```

Prove that these points are antipodes. The `distance` function shows them to be 180 degrees apart.


```
dist = distance(mwlat,mwlon,amwlat,amwlon)
dist = 180.0000
```

Generate a map centered on the original point and then another map centered on the antipode.

```
figure
subplot(1,2,1)
axesm ('MapProjection','ortho','origin',[mwlát mwlón],...
       'frame','on','grid','on')
load coastlines
geoshow(coastlat,coastlon,'displaytype','polygon')
geoshow(mwlát,mwlón,'Marker','o','Color','red')
title(sprintf('Looking down at\n(%s,%s)', ...
             angl2str(mwlát,'ns'), angl2str(mwlón,'ew'))))

subplot(1,2,2)
axesm ('MapProjection','ortho','origin',[amwlát amwlón],...
       'frame','on','grid','on')
geoshow(coastlat,coastlon,'displaytype','polygon')
geoshow(amwlát,amwlón,'Marker','o','Color','red')
title(sprintf('Looking down at\n(%s,%s)', ...
             angl2str(amwlát,'ns'), angl2str(amwlón,'ew'))))
```

Looking down at
(42.30° N , 71.35° W)



Looking down at
(42.30° S , 108.65° E)



Introduced before R2006a

append

Append features to geographic or planar vector

Syntax

```
vout = append(vin, lat, lon)
vout = append(vin, x, y)
vout = append( ____, field, value)
```

Description

`vout = append(vin, lat, lon)` appends the latitude and longitude values in `lat` and `lon` to the `Latitude` and `Longitude` properties of the geographic vector `vin`. `vin` is either a `geopoint` or a `geoshape` object.

`vout = append(vin, x, y)` appends the planar x- and y-coordinates in `x` and `y` to the `X` and `Y` properties of the planar vector `vin`. `vin` is either a `mappoint` or a `mapshape` object.

`vout = append(____, field, value)` appends the values specified in `value` to the corresponding dynamic property, `field`. If the property does not exist, `append` adds the dynamic property to the object using the value of `field` for the name and assigning the field the value specified in `value`. You can specify multiple field-value pairs. Enclose each field name in single quotes.

Examples

Append Points to Geopoint Vector

Create a geopoint vector.

```
p = geopoint(42, -110)
p =
  1x1 geopoint vector with properties:
```



```

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: 42
  Longitude: -110

```

Append the vector with three new geographic points.

```

lat1 = [42.1 44 44.1];
lon1 = [-101 -120 -121];
p = append(p,lat1,lon1)

```

```

p =
4x1 geopoint vector with properties:

```

```

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: [42 42.1000 44 44.1000]
  Longitude: [-110 -101 -120 -121]

```

The length of the geopoint vector increases by three, as expected, and the 'Latitude' and 'Longitude' feature properties list the new coordinates.

Append Points to Mapshape Vector

Create a mapshape vector, designating a dynamic 'Temperature' property. This vector has one feature with three vertices.

```

s = mapshape(42:44,30:32,'Temperature', {65:67})

```

```

s =
1x1 mapshape vector with properties:

```

```

Collection properties:
  Geometry: 'line'
  Metadata: [1x1 struct]

```

```
Vertex properties:
      X: [42 43 44]
      Y: [30 31 32]
Temperature: [65 66 67]
```

Append the vector with two new planar points. The points are stored as a new feature with two vertices.

```
x1 = [44.5 45];
y1 = [32.5 33];
s = append(s,x1,y1)

s =
2x1 mapshape vector with properties:

Collection properties:
      Geometry: 'line'
      Metadata: [1x1 struct]
Vertex properties:
(2 features concatenated with 1 delimiter)
      X: [42 43 44 NaN 44.5000 45]
      Y: [30 31 32 NaN 32.5000 33]
Temperature: [65 66 67 NaN 0 0]
```

The features are separated by NaN. The 'Temperature' value of the new points is set to 0 by default, since no value was specified during the call to `append`. The mapshape vector grew from 1x1 to 2x1 in length because the number of features increased.

Append Point with New Property to Mappoint Vector

Create a mappoint vector with a dynamic property Temperature.

```
mp = mappoint(42,-110,'Temperature',65)

mp =
1x1 mappoint vector with properties:

Collection properties:
      Geometry: 'point'
      Metadata: [1x1 struct]
```

```
Feature properties:
  X: 42
  Y: -110
  Temperature: 65
```

Add a point to this vector. The point contains a new dynamic property, Pressure.

```
mp = append(mp,42.2, -110.5, 'Temperature',65.6, 'Pressure', 100.0)
```

```
mp =
2x1 mappoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  X: [42 42.2000]
  Y: [-110 -110.5000]
  Temperature: [65 65.6000]
  Pressure: [0 100]
```

A default Pressure value of 0 is automatically added to the first point.

Append Points with New Properties to Geoshape Vector

Create a geoshape vector, designating a dynamic 'Temperature' property. The 'Temperature' values are input as a cell array so that they belong to a single feature. This vector has one feature with three vertices.

```
lat1 = [42, 42.2, 43];
lon1 = [-110, -110.3, -110.5];
temp1 = {[65, 65.1, 65.2]};
s = geoshape(lat1,lon1, 'Temperature',temp1)
```

```
s =
1x1 geoshape vector with properties:
```

```
Collection properties:
  Geometry: 'line'
  Metadata: [1x1 struct]
Vertex properties:
  Latitude: [42 42.2000 43]
```

```
Longitude: [-110 -110.3000 -110.5000]
Temperature: [65 65.1000 65.2000]
```

Add three points to the geoshape vector, including a two new dynamic properties 'Precipitation' and 'CloudCover'. The latitude and longitude values are added as a two-element cell array, so two features are added to the geoshape vector. Note that the 'Temperature' and 'Precipitation' values are specified as two-element vectors, while the new 'CloudCover' values are specified as a one-element cell array.

```
lat2 = {[50 50.2],60};
lon2 = {[-120 -121],-130};
temp2 = [60.2 60.4];
precip = [0.07 0.19];
cloud = {[20,80]};
s2 = append(s,lat2,lon2,'Temperature',temp2,'Precipitation',precip,'CloudCover',cloud)

s2 =
3x1 geoshape vector with properties:

Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
Vertex properties:
(3 features concatenated with 2 delimiters)
    Latitude: [42 42.2000 43 NaN 50 50.2000 NaN 60]
    Longitude: [-110 -110.3000 -110.5000 NaN -120 -121 NaN -130]
    Temperature: [65 65.1000 65.2000 NaN 60.2000 0 NaN 60.4000]
    CloudCover: [0 0 0 NaN 20 80 NaN 0]
Feature properties:
    Precipitation: [0 0.0700 0.1900]
```

This appended vector `s2` now has three features, separated by `NaN`, with some Vertex properties and some Feature properties. The two cells of the latitude and longitude cell arrays form the two newly-added features, one with two vertices and the other with one vertex. Since 'Temperature' had previously been designated as a Vertex property in `s`, the new 'Temperature' values are added as Vertex properties. The 'Temperature' value of one new point has not been assigned, so it is set to the default value of 0.

However, the new 'Precipitation' and 'CloudCover' properties are designated as a Vertex or Feature property, whichever is more appropriate for the value format. 'Precipitation' values are provided as a two-element vector, so they are assigned as Feature properties, where each element of `precip2` belongs to a separate feature of the

geoshape vector. Since 'CloudCover' values are provided as a cell array, the values must belong to the same feature, so they are set as Vertex properties corresponding to the first added feature. No 'CloudCover' values have been specified for the second added feature, so vertices in the second feature are assigned the default value 0. Finally, 'Precipitation' and 'CloudCover' values for the original feature are set to the default value of 0.

Input Arguments

vin — Input geographic or planar vector

geopoint, geoshape, mappoint, or mapshape object

Input geographic or planar vector, specified as a geopoint, geoshape, mappoint, or mapshape object.

lat — Latitude values

numeric scalar or vector

Latitude values, specified as a numeric scalar or vector.

Data Types: single | double

lon — Longitude values

numeric scalar or vector

Longitude values, specified as a numeric scalar or vector.

Data Types: single | double

x — Planar x-coordinates

numeric scalar or vector

Planar x-coordinates, specified as a numeric scalar or vector.

Data Types: single | double

y — Planar y-coordinates

numeric scalar or vector

Planar y-coordinates, specified as a numeric scalar or vector.

Data Types: single | double

field — Field name

string scalar | character vector

Field name, specified as a string scalar or character vector. `Field` can specify the name of an existing property in the vector data, or the name you want assigned to a new property that you want to add to the vector data.

Data Types: `char` | `string`

value — Value you want to assign to the property specified by `field`

cell array | scalar | vector

Value you want to assign to the property specified by `field`, specified as a cell array, or a scalar or vector of any numeric class or logical.

- When `value` is a cell array, `append` adds the property as a Vertex property.
- When `value` is a numeric array, `append` adds the property as a Feature property.
- When `value` is empty, `append` removes the property.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64` | `logical` | `char` | `string` | `cell`

Output Arguments

vout — Output geographic or planar vector

`geopoint`, `geoshape`, `mappoint`, or `mapshape` object

Output geographic or planar vector, returned as a `geopoint`, `geoshape`, `mappoint`, or `mapshape` object. The object type of `vout` matches the object type of `vin`.

See Also

`cat`

Introduced in R2012a

arcgridread

Read gridded data set in ArcGrid ASCII or GridFloat format

Syntax

```
[Z,R] = arcgridread(filename)
[Z,R] = arcgridread(filename,coordinateSystemType)
```

Description

`[Z,R] = arcgridread(filename)` imports a grid in either ArcGrid ASCII or GridFloat format from the file specified by `filename`. Returns `Z`, a 2-D array containing the data values, and raster referencing information in `R`. If the input file is accompanied by a projection file (with extension `.prj` or `.PRJ`), then `R` is a raster reference object whose type matches the coordinate reference system defined in the projection file. Otherwise `R` is a referencing matrix.

`[Z,R] = arcgridread(filename,coordinateSystemType)` returns `R` as a raster reference object whose type is consistent with the value specified by `coordinateSystemType`. This optional input argument can be helpful in the absence of a projection file. The function throws an error if a projection file is present and `coordinateSystemType` contradicts the type of coordinate reference system defined in the projection file.

Examples


Load and View Mount Washington Terrain Elevation Data

Read the data.

```
[Z,R] = arcgridread('MtWashington-ft.grd');
```


Display the data as a surface. Add two labels to the display and set the colormap.

```
mapshow(Z,R, 'DisplayType', 'surface')  
xlabel('x (easting in meters)')  
ylabel('y (northing in meters)')  
demcmap(Z)
```



View the terrain in 3-D.

```
axis normal  
view(3)  
axis equal  
grid on  
zlabel('elevation in feet')
```

Input Arguments

filename — Name of file containing the grid
character vector

Name of file containing the grid, specified as a character vector. The `arcgridread` function supports the following formats.

| Format | Description |
|---------------|--|
| ArcGrid ASCII | In this format, created by the ArcGIS GRIDASCII command, the data and header information are in a single text file. <code>arcgridread</code> will also read a <code>.prj</code> file, if one is present. This format is also known as Arc ASCII Grid or ESRI ASCII Raster format. |
| GridFloat | In this format, created by the ArcGIS GRIDFLOAT command, data and header information are in separate files (<code>.flt</code> and <code>.hdr</code>). Specify the name of the <code>.flt</code> file (including the file extension). <code>arcgridread</code> will also read a <code>.prj</code> file, if one is present. This format is also known as ESRI GridFloat. |

Data Types: char

coordinateSystemType — Coordinate system type identifier

'auto' (default) | 'geographic' | 'planar'

Coordinate system type identifier, specified as one of the following values.

| Type Identifier | Description |
|------------------------|---|
| 'geographic' | Returns a geographic cells reference object appropriate to a latitude/longitude system. |
| 'planar' | Returns a map cells reference object appropriate to a projected map coordinate system. |
| 'auto' | Type of raster reference object determined by the file contents. |

Data Types: char

Output Arguments

Z — Gridded data set

2-D array

Gridded data set, returned as a 2-D array. The class of the array depends on the format of the data, described in the following table. `arcgridread` assigns NaN to elements of Z corresponding to null data values in the grid file.

| Format | Class of Returned Gridded Data |
|---------------|--|
| ArcGrid ASCII | 2-D array of class <code>double</code> . |
| GridFloat | 2-D array of class <code>single</code> . |

R — Raster referencing information

raster reference object | referencing matrix

Raster referencing information, returned as a raster reference object whose type matches the coordinates reference system defined in the projection file. If no projection file exists and you do not specify the `coordinateSystemType` parameter, `R` is a referencing matrix.

Tips

- The `arcgridread` function does not import data in the ArcGrid Binary format (also known as ArcGrid, Arc/INFO Grid, and ESRI ArcInfo Grid). ArcGIS uses this format internally and it uses multiple files in a folder with standard names such as `hdr.adf` and `w001001.adf`.

See Also

`geotiffread` | `sdtsemread` | `worldfileread`

Introduced before R2006a

areaint

Surface area of polygon on sphere or ellipsoid

Syntax

```
area = areaint(lat,lon)
area = areaint(lat,lon,ellipsoid)
area = areaint(lat,lon,units)
area = areaint(lat,lon,ellipsoid,units)
```

Description

`area = areaint(lat,lon)` calculates the spherical surface area of the polygon specified by the input vectors `lat` and `lon`. The calculation uses a line integral approach. The output, `area`, is the fraction of surface area covered by the polygon on a unit sphere. To supply multiple polygons, separate the polygons by NaNs in the input vectors. Accuracy of the integration method is inversely proportional to the distance between `lat/lon` points.

`area = areaint(lat,lon,ellipsoid)` calculates the surface area of the polygon on the ellipsoid or sphere defined by the input `ellipsoid`, which can be a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. The output, `area`, is in squares units corresponding to the units of `ellipsoid`.

`area = areaint(lat,lon,units)` uses the units defined by `units`, the string scalar or character vector `'degrees'` or `'radians'`. If omitted, default units of degrees are assumed.

`area = areaint(lat,lon,ellipsoid,units)` uses both the inputs `ellipsoid` and `units` in the calculation.

Examples

Consider the area enclosed by a 30° lune from pole to pole and bounded by the prime meridian and 30°E . You can use the function `areaquad` to get an exact solution:

```
area = areaquad(90,0,-90,30)
area =
    0.0833
```

This is $1/12$ the spherical area. The more points used to define this polygon, the more integration steps `areaint` takes, improving the estimate. This first attempt takes a point every 30° of latitude:

```
lats = [-90:30:90,60:-30:-60]';
lons = [zeros(1,7), 30*ones(1,5)]';
area = areaint(lats,lons)
area =
    0.0792
```


Now, calculate a better estimate, with one point every 1° of latitude:

```
lats = [-90:1:90,89:-1:-89]';
lons = [zeros(1,181), 30*ones(1,179)]';
area = areaint(lats,lons)
area =
    0.0833
```

Algorithms

This function enables the measurement of areas enclosed by arbitrary polygons. This is a numerical estimate, using a line integral based on Green's Theorem. As such, it is limited by the accuracy and resolution of the input data.

Areas are computed for arbitrary polygons on the ellipsoid or sphere



An area is returned for each NaN-separated polygon

Given sufficient data, the `areaInt` function is the best method for determining the areas of complex polygons, such as continents, cloud cover, and other natural or derived features. The calculations in this function employ a spherical Earth assumption. For nonspherical ellipsoids, the latitude data is converted to the auxiliary authalic sphere.

See Also

`almanac` | `areamat` | `areaquad`

Introduced before R2006a

areamat

Surface area covered by nonzero values in binary data grid

Syntax

```
A = areamat(BW,R)
A = areamat(BW,refvec,ellipsoid)
[A, cellarea] = areamat(...)
```

Description

`A = areamat(BW,R)` returns the surface area covered by the elements of the binary regular data grid `BW`, which contain the value 1 (true). `BW` can be the result of a logical expression such as `BW = (topo > 0)`. `R` can be a geographic raster reference object, a referencing vector, or a referencing matrix.

If `R` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(BW)` and its `RasterInterpretation` must be 'cells'.

If `R` is a referencing vector, it must be a 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If `R` is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to or from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If `R` is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. Nearest-neighbor interpolation is used by default. NaN is returned for points outside the grid limits or for which `lat` or `lon` contain NaN. All angles are in units of degrees.

The output `A` expresses surface area as a fraction of the surface area of the unit sphere (4π), so the result ranges from 0 to 1.

`A = areamat(BW,refvec,ellipsoid)` calculates the surface area on the ellipsoid or sphere defined by the input `ellipsoid`, which can be a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. The units of the output, `A`, are the square of the length units in which the semimajor axis is provided. For example, if `ellipsoid` is replaced with `wgs84Ellipsoid('kilometers')`, then `A` is in square kilometers.

`[A, cellarea] = areamat(...)` returns a vector, `cellarea`, describing the area covered by the data cells in `BW`. Because all the cells in a given row are exactly the same size, only one value is needed per row. Therefore `cellarea` has size `M-by-1`, where `M = size(BW,1)` is the number of rows in `BW`.

Examples

```
load topo
area = areamat((topo>127),topolegend)
```

```
area =
    0.2411
```

Approximately 24% of the Earth has an altitude greater than 127 meters. The surface area of this portion of the Earth in square kilometers if a spherical ellipsoid is:

```
earth = referenceSphere('earth', 'km');
area = areamat((topo>127),topolegend,earth)
```

```
area =
    1.2299e+08
```

To illustrate the `cellarea` output, consider a smaller map:

```
BW = ones(9,18);
refvec = [.05 90 0] % each cell 20x20 degrees
[area,cellarea] = areamat(BW,refvec)
```

```
area =
    1.0000
cellarea =
    0.0017
    0.0048
    0.0074
    0.0091
```



```
0.0096
0.0091
0.0074
0.0048
0.0017
```

Each entry of `cellarea` represents the portion of the unit sphere's total area a cell in that row of `BW` would contribute. Since the column extends from pole to pole in this case, it is symmetric.

Tips

Given a regular data grid that is a logical 0-1 matrix, the `areamat` function returns the area corresponding to the true, or 1, elements. The input data grid can be a logical statement, such as `(topo>0)`, which is 1 everywhere that `topo` is greater than 0 meters, and 0 everywhere else. This is an illustration of that matrix:



This calculation is based on the `areaquad` function and is therefore limited only by the granularity of the cellular data.

See Also

`areaint` | `areaquad`

Introduced before R2006a

areaquad

Surface area of latitude-longitude quadrangle

Syntax

```
area = areaquad(lat1,lon1,lat2,lon2)
area = areaquad(lat1,lon1,lat2,lon2,ellipsoid)
area = areaquad(lat1,lon1,lat2,lon2,ellipsoid,units)
```

Description

`area = areaquad(lat1,lon1,lat2,lon2)` returns the surface area bounded by the parallels `lat1` and `lat2` and the meridians `lon1` and `lon2`. The output `area` is a fraction of the unit sphere's area of 4π , so the result ranges from 0 to 1.

`area = areaquad(lat1,lon1,lat2,lon2,ellipsoid)` allows the specification of the ellipsoid model with `ellipsoid`. `ellipsoid` is a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. When `ellipsoid` is input, the resulting `area` is given in terms of the (squared) units of the ellipsoid. For example, if the ellipsoid `referenceEllipsoid('grs80','kilometers')` is used, the resulting `area` is in km^2 .

`area = areaquad(lat1,lon1,lat2,lon2,ellipsoid,units)` where `units` specifies the units of the inputs. The default is `'degrees'`.

Examples

Find the fraction of the Earth's surface that lies between 30°N and 45°N, and also between 25°W and 60°E:

```
area = areaquad(30,-25,45,60)

area =
    0.0245
```

Assuming a spherical ellipsoid, find the surface area of the Earth in square kilometers.

```
earthellipsoid = referenceSphere('earth','km');  
area = areaquad(-90,-180,90,180,earthellipsoid)
```

```
area =  
    5.1006e+08
```

For comparison,


```
earthellipsoid.SurfaceArea
```

```
ans =  
    5.1006e+08
```

Definitions

Latitude-Longitude Quadrangle

A latitude-longitude quadrangle is a region bounded by two meridians and two parallels. In spherical geometry, it is the intersection of a *lune* (a section bounded by two meridians) and a *zone* (a section bounded by two parallels).



Algorithms

The `areaquad` calculation is exact, being based on simple spherical geometry. For nonspherical ellipsoids, the data is converted to the auxiliary authalic sphere.

See Also

`almanac` | `areaint` | `areamat`

Introduced before R2006a

map.geodesy.AuthalicLatitudeConverter

Convert between geodetic and authalic latitudes

Description

An `AuthalicLatitudeConverter` object provides conversion methods between geodetic and authalic latitudes for an ellipsoid with a given eccentricity.

The authalic latitude maps an ellipsoid (oblate spheroid) to a sphere while preserving surface area. Use authalic latitudes when implementing equal area map projections on the ellipsoid.

Creation

Syntax

```
converter = map.geodesy.AuthalicLatitudeConverter  
converter = map.geodesy.AuthalicLatitudeConverter(spheroid)
```

Description

`converter = map.geodesy.AuthalicLatitudeConverter` creates an `AuthalicLatitudeConverter` object for a sphere and sets the `Eccentricity` to 0.

`converter = map.geodesy.AuthalicLatitudeConverter(spheroid)` creates an authalic latitude converter object and sets the `Eccentricity` property to match the specified spheroid object.

Input Arguments

spheroid — Reference spheroid

referenceEllipsoid | oblateSpheroid | referenceSphere

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. To create a spheroid object, use the creation function specific to the object, or the `wgs84Ellipsoid` function.

Example: `spheroid = referenceEllipsoid('GRS 80');`

Properties

Eccentricity — Ellipsoid eccentricity

0 | numeric scalar

Ellipsoid eccentricity, specified as a numeric scalar. Eccentricity is in the interval [0, 0.5]. Eccentricities larger than 0.5 are possible in theory, but do not occur in practice and are not supported.

Data Types: `double`

Object Functions

`forward` Convert geodetic latitude to authalic, conformal, isometric, or rectifying latitude
`inverse` Convert authalic, conformal, isometric, or rectifying latitude to geodetic latitude

Examples

Create an Authalic Converter

Create a Geodetic Reference System 1980 (`grs80`) reference ellipsoid.

```
grs80 = referenceEllipsoid('GRS 80');
```

Create an authalic converter object and set the value of the `Eccentricity` property.

```
conv1 = map.geodesy.AuthalicLatitudeConverter;  
conv1.Eccentricity = grs80.Eccentricity
```

```
conv1 =
```

`AuthalicLatitudeConverter` with properties:

`Eccentricity: 0.0818`

Create an Authalic Converter Specifying a Spheroid

Create a reference ellipsoid.

```
grs80 = referenceEllipsoid('GRS 80');
```

Create an authalic latitude converter object based on the ellipsoid.

```
conv2 = map.geodesy.AuthalicLatitudeConverter(grs80)
```

```
conv1 =
```

`AuthalicLatitudeConverter` with properties:

`Eccentricity: 0.0818`

See Also

Functions

`geocentricLatitude` | `parametricLatitude`

Objects

`ConformalLatitudeConverter` | `IsometricLatitudeConverter` |
`RectifyingLatitudeConverter`

Introduced in R2013a

avhrrgoode

Read AVHRR data product stored in Goode Projection

Syntax

```
[latgrat, longrat, z] = avhrrgoode(region, filename)
[...] = avhrrgoode(region, filename, scalefactor)
[...] = avhrrgoode(region, filename, scalefactor, latlim, lonlim)
[...] = avhrrgoode(region, filename, scalefactor, latlim, lonlim, gsize)
[...] =
avhrrgoode(region, filename, scalefactor, latlim, lonlim, gsize, ...
nrows, ncols)
[...] =
avhrrgoode(region, filename, scalefactor, latlim, lonlim, gsize, ...
nrows, ncols, resolution)
[...] =
avhrrgoode(region, filename, scalefactor, latlim, lonlim, gsize, ...
nrows, ncols, resolution, precision)
```

Description

[latgrat, longrat, z] = avhrrgoode(region, filename) reads data from an Advanced Very High Resolution Radiometer (AVHRR) data set with a nominal resolution of 1 km that is stored in the Goode projection. Data in this format includes a nondimensional vegetation index (NDVI) and Global Land Cover Characteristics (GLCC) data sets. region specifies the geographic coverage of the file, using the following values:

- 'g' or 'global'
- 'af' or 'africa'
- 'ap' or 'australia/pacific'
- 'ea' or 'eurasia'
- 'na' or 'north america'

- 'sa' or 'south america'

filename is a string scalar or character vector specifying the name of the data file. Output Z is a geolocated data grid with coordinates latgrat and longrat in units of degrees. Z, latgrat, and longrat are of class double. Projected coordinates that lie within the interrupted areas of the projection are set to NaN. A scale factor of 100 is applied to the original data set, so that Z contains every 100th point in both X and Y directions.

[...] = avhrrgoode(region, filename, scalefactor) uses the integer scalefactor to downsample the data. A scale factor of 1 returns every point. A scale factor of 10 returns every 10th point. The default value is 100.

[...] = avhrrgoode(region, filename, scalefactor, latlim, lonlim) returns data for the specified region. The returned data can extend somewhat beyond the requested area. Limits are two-element vectors in units of degrees, with latlim in the range [-90 90] and lonlim in the range [-180 180]. latlim and lonlim must be ascending. If latlim and lonlim are empty, the entire area covered by the data file is returned. If the quadrangle defined by latlim and lonlim (when projected to form a polygon in the appropriate Goode projection) fails to intersect the bounding box of the data in the projected coordinates, then Z, latgrat, and longrat are returned as empty.

[...] = avhrrgoode(region, filename, scalefactor, latlim, lonlim, gsize) controls the size of the graticule matrices. gsize is a two-element vector containing the number of rows and columns desired. By default, latgrat, and longrat have the same size as Z.

[...] = avhrrgoode(region, filename, scalefactor, latlim, lonlim, gsize, ... nrows, ncols) overrides the dimensions for the standard file format for the selected region. This syntax is useful for data stored on CD-ROM, which may have been truncated to fit. Some global data sets were distributed with 16347 rows and 40031 columns of data on CD-ROMs. The default size for global data sets is 17347 rows and 40031 columns of data.

[...] = avhrrgoode(region, filename, scalefactor, latlim, lonlim, gsize, ... nrows, ncols, resolution) reads a data set with the spatial resolution specified in meters. Specify resolution as either 1000 or 8000 (meters). If empty, the full resolution of 1000 meters is assumed. Data is also available at 8000-meter resolution. Nondimensional vegetation index data at 8-km spatial resolution has 2168 rows and 5004 columns.

```
[...] =  
avhrrgoode(region, filename, scalefactor, latlim, lonlim, gsize, ...  
nrows, ncols, resolution, precision) reads a data set expecting the integer  
precision specified. If empty, 'uint8' is assumed. 'uint16' is appropriate for some  
files. Check the metadata (.txt or README) file in the GLCC ftp folder for specification  
of the file format and contents. In either case, Z is converted to class double.
```

Background

The United States maintains a family of satellite-based sensors to measure climate change under the Earth Observing System (EOS) program. The precursors to the EOS data are the data sets produced by NOAA and NASA under the Pathfinder program. These are data derived from the Advanced High Resolution Radiometer sensor flown on the NOAA Polar Orbiter satellites, NOAA-7, -9, and -11, and have spatial resolutions of about 1 km. The data from the AVHRR sensor is processed into separate land, sea, and atmospheric indices. Land area data is processed to a nondimensional vegetation index (NDVI) or land cover classification and stored in binary files in the Plate Carrée, Goode, and Lambert projections. Sea data is processed to surface temperatures and stored in HDF formats. `avhrrgoode` reads land data saved in the Goode projection with global and continental coverage at 1 km. It can also read 8 km data with global coverage.

Limitations

Most files store the data in scaled integers. Though this function returns the data as double, the scaling from integer to float is not performed. Check the data's README file for the appropriate scaling parameters.

Examples

Example 1 — Downsampled Classified Global GLCC Coverage

Read and display every 50th point from the Global Land Cover Characteristics (GLCC) file covering the entire globe with the USGS classification scheme, named `gusgs2_0g.img`. (To run the example, you must first download the file.)

```
[latgrat, longrat, Z] = avhrrgoode('global', ...  
    'gusgs2_0g.img', 50);
```


```

% Convert the geolocated data grid to an geolocated image.
uniqueClasses = unique(Z);
RGB = ind2rgb8(uint8(Z), jet(numel(uniqueClasses)));

% Display the data as an image using the Goode projection.
origin = [0 0 0];
ellipsoid = [6370997 0];
figure
axesm('MapProjection', 'goode', 'Origin', origin, ...
      'Geoid', ellipsoid)
geoshow(latgrat, longrat, RGB, 'DisplayType', 'image');
axis image off

% Plot the coastlines.
hold on
load coastlines
plotm(coastlat,coastlon)

```



Example 2 — Classified GLCC Data for California


Read and display every point from the Global Land Cover Characteristics (GLCC) file covering California with the USGS classification scheme, named `nausgs1_2g.img`. You must first download the file to run this example.

```

figure
usamap california
mstruct = gcm;

```

```
latlim = mstruct.maplatlimit;  
lonlim = mstruct.maplonlimit;  
scalefactor = 1;  
[latgrat, longrat, Z] = ...  
    avhrrgoode('na', 'nausgs1_2g.img', scalefactor, latlim, lonlim);  
geoshow(latgrat, longrat, Z, 'DisplayType', 'texturemap');  
  
% Overlay vector data from usastatehi.shp.  
california = shaperead('usastatehi', 'UseGeoCoords', true, ...  
    'BoundingBox', [lonlim;latlim]);  
geoshow([california.Lat], [california.Lon], 'Color', 'black');
```



Tips

This function reads the binary files as is. You should not use byte-swapping software on these files.

The AVHRR project and data sets are described in and provided by various U.S. Government Web sites. See the entry for Global Land Cover Characteristics (GLCC) in the tech note referred to below.

Note For details on locating map data for download over the Internet, see the following documentation at the MathWorks Web site: "Find Geospatial Data Online".

See Also

avhrrlambert

Introduced before R2006a

avhrrlambert

Read AVHRR data product stored in eqaazim projection

Syntax

```
[latgrat,longrat,Z] = avhrrlambert(region,filename)  
[...] = avhrrlambert(region,filename, scalefactor)  
[...] = avhrrlambert(region,filename, scalefactor, latlim, lonlim)  
[...] = avhrrlambert(region,filename, scalefactor, latlim, lonlim,  
gsize)  
[...] = avhrrlambert(region,filename, scalefactor, latlim, lonlim,  
gsize,precision)
```

Description

[*latgrat,longrat,Z*] = *avhrrlambert(region,filename)* reads data from an Advanced Very High Resolution Radiometer (AVHRR) data set with a nominal resolution of 1 km that is stored in the Lambert Equal Area Azimuthal projection. Data of this type includes the Global Land Cover Characteristics (GLCC). *region* specifies the coverage of the file. Valid regions are listed in the following table. *filename* is a string specifying the name of the data file. *Z* is a geolocated data grid with coordinates *latgrat* and *longrat* in units of degrees. A scale factor of 100 is applied to the original data set such that *Z* contains every 100th point in both X and Y.

| Region Specifiers |
|-----------------------------|
| 'a' or 'asia' |
| 'af' or 'africa' |
| 'ap' or 'australia/pacific' |
| 'e' or 'europe' |
| 'na' or 'north america' |
| 'sa' or 'south america' |

[...] = avhrrlambert(*region, filename, scalefactor*) uses the integer *scalefactor* to downsample the data. A scale factor of 1 returns every point. A scale factor of 10 returns every 10th point. The default value is 100.

[...] = avhrrlambert(*region, filename, scalefactor, latlim, lonlim*) returns data for the specified region. The result may extend somewhat beyond the requested area. The limits are two-element vectors in units of degrees, with *latlim* in the range [-90 90] and *lonlim* in the range [-180 180]. If *latlim* and *lonlim* are empty, the entire area covered by the data file is returned. If the quadrangle defined by *latlim* and *lonlim* (when projected to form a polygon in the appropriate Lambert Equal Area Azimuthal projection) fails to intersect the bounding box of the data in the projected coordinates, then *latgrat*, *longrat*, and *Z* are empty.

[...] = avhrrlambert(*region, filename, scalefactor, latlim, lonlim, gsize*) controls the size of the graticule matrices. *gsize* is a two-element vector containing the number of rows and columns desired. If omitted or empty, a graticule the size of the grid is returned.

[...] = avhrrlambert(*region, filename, scalefactor, latlim, lonlim, gsize, precision*) reads a data set with the integer *precision* specified. If omitted, 'uint8' is assumed. 'uint16' is appropriate for some files. Check the metadata (.txt or README) file in the ftp folder for specification of the file format and contents.

Background

The United States plans to build a family of satellite-based sensors to measure climate change under the Earth Observing System (EOS) program. Early precursors to the EOS data are the data sets produced by NOAA and NASA under the Pathfinder program. These are data derived from the Advanced High Resolution Radiometer sensor flown on the NOAA Polar Orbiter satellites, NOAA-7, -9, and -11 with a spatial resolution of about 1 km. The data from the AVHRR sensor is processed into separate land, sea, and atmospheric indices. Land area data is processed to a nondimensional vegetation index or land cover classification and stored in binary files in the Plate Carrée, Goode, and Lambert Equal Area Azimuthal projections. Sea data is processed to surface temperatures and stored in HDF formats. This function reads land cover data for the continents saved in the Lambert Equal Area Azimuthal projection at 1 km.

Examples


Example 1

Read and display every 100th point from the Global Land Cover Characteristics (GLCC) file covering North America with the USGS classification scheme, named `nausgs1_2l.img`.

```
[latgrat, longrat, Z] = avhrrlambert('na', 'nausgs1_2l.img');
```

Display the data using the Lambert Equal Area Azimuthal projection.

```
origin = [50 -100 0];  
ellipsoid = [6370997 0];  
figure  
axesm('MapProjection', 'eqaazim', 'Origin', ...  
      origin, 'Geoid', ellipsoid)  
geoshow(latgrat, longrat, Z, 'DisplayType', 'texturemap');
```




Example 2

Read and display every other point from the Global Land Cover Characteristics (GLCC) file covering Europe with the USGS classification scheme, named `eausgs1_2le.img`.


```

figure
worldmap france
mstruct = gcm;
latlim = mstruct.maplatlimit;
lonlim = mstruct.maplonlimit;
scalefactor = 2;
[latgrat, longrat, Z] = avhrrlambert('e', 'eaugs1_2le.img', ...
    scalefactor, latlim, lonlim);
geoshow(latgrat, longrat, Z, 'DisplayType', 'texturemap');
geoshow('landareas.shp', 'FaceColor', 'none', 'EdgeColor', 'black')

```



Tips

This function reads the binary files as is. You should not use byte-swapping software on these files.

The AVHRR project and data sets are described in and provided by various U.S. Government Web sites.

Note For details on locating map data for download over the Internet, see the following documentation at the MathWorks Web site: “Find Geospatial Data Online”.

See Also

avhrrgoode

Introduced before R2006a

axes2ecc

Eccentricity of ellipse from axes lengths

Note Support for nonscalar input, including the syntax `ecc = axes2ecc(vec)`, will be removed in a future release.

Syntax

```
ecc = axes2ecc(semimajor,semiminor)
ecc = axes2ecc(vec)
```

Description

`ecc = axes2ecc(semimajor,semiminor)` computes the eccentricity of an ellipse (or ellipsoid of revolution) given the semimajor and semiminor axes. The input data can be scalar or matrices of equal dimensions.

`ecc = axes2ecc(vec)` assumes a 2 element vector (`vec`) is supplied, where `vec = [semimajor semiminor]`.

See Also

`ecc2flat` | `ecc2n` | `majaxis` | `minaxis`

Introduced before R2006a

axesm

Create map axes

The `axesm` function creates a map axes into which both vector and raster geographic data can be projected using functions such as `plotm` and `geoshow`. Properties specific to map axes can be assigned upon creation with `axesm`, and for an existing map axes they can be queried and changed using `getm` and `setm`. Use the standard `get` and `set` methods to query and control the standard MATLAB axes properties of a map axes.

Map axes are standard MATLAB axes with different default settings for some properties and a MATLAB structure for storing projection parameters and other data. The main differences in default settings are:

- Axes properties `XGrid`, `YGrid`, `XTick`, `YTick` are set to `'off'`.
- The `hold` mode is `'on'`.

The map projection structure stores the map axes properties, which, in addition to the special standard axes settings, allow Mapping Toolbox functions to recognize an axes or an opened FIG-file as a map axes. See [Map Axes Properties](#) for descriptions of the map axes properties.

Syntax

```
axesm  
axesm(Name,Value)  
axesm(projid,Name,Value)
```

Description

`axesm` with no input arguments, initiates the `axesmui` map axes graphical user interface, which can be used to set map axes properties. This is detailed on the [axesmui](#) reference page.

`axesm(Name,Value)` creates a map axes and modifies the map axes appearance using name-value pairs to set properties. You can specify multiple name-value pairs. Enclose each property name in quotes. For example, `'FontSize',14` sets the font size for the

map axes text. Properties may be specified in any order, but the `MapProjection` property must be included. For a full list of properties, see [Map Axes Properties](#).

`axesm(projid,Name,Value)` specifies which map projection to use. `projid` should match one of the entries in the last column displayed by the `maps` function. You can also find these listed in “[Summary and Guide to Projections](#)”.

Examples

Create Map Axes for Mercator Projection

Create map axes for a Mercator projection, with selected latitude limits:

```
axesm('MapProjection','mercator','MapLatLimit',[-70 80])
```

In the preceding example, all properties not explicitly addressed in the call are set to either fixed or calculated defaults. The file `mercator.m` defines a projection function, so the same result could have been achieved with the function

```
axesm('mercator','MapLatLimit',[-70 80])
```

Each projection function includes default values for all properties. Any following property name/property value pairs are treated as overrides.

In either of the above examples, data displayed in the given map axes is in a Mercator projection. Any data falling outside the prescribed limits is not displayed.

Input Arguments

projid — Map projection ID

character vector | string scalar

Map projection ID, specified as a string scalar or character vector. `projid` should match one of the entries in the last column displayed by the `maps` function. You can also find these listed in “[Summary and Guide to Projections](#)”.

Note The names of projection files are case sensitive. The projection files included in Mapping Toolbox software use only lowercase letters and Arabic numerals.

Example: 'eqdcylin'

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, . . . , NameN, ValueN`.

Example: `axesm('MapProjection', 'pcarree', 'Frame', 'on')` creates a map axes with a Plate Carree projection, and makes the map frame visible.

Note The properties listed here are only a subset. For a full list, see [Map Axes Properties](#).

MapProjection — Map projection

character vector | string scalar

Map projection, specified as a string scalar or character vector. `MapProjection` sets the projection, and hence all transformation calculations, for the map axes object. It must be a member of the recognized projection set, which you can list by typing `getm('MapProjection')` or `maps`. For more information on projections, see the *Mapping Toolbox User's Guide*. Some projections set their own defaults for other properties, such as parallels and trim limits.

MapLatLimit — Geographic latitude limits of the display area

two-element vector

Geographic latitude limits of the display area, specified as a two-element vector of the form `[southern_limit northern_limit]`. This property can be set for many typical projections and geometries, but cannot be used with oblique projections or with `globe`, for example.

When applicable, the `MapLatLimit` property may affect the origin latitude if the `Origin` property is not set explicitly when calling `axesm`. It may also determine the value used for `FLatLimit`. See “Access and Change Map Axes Properties” for a more complete description of the applicability of `MapLatLimit` and its interaction with the origin, frame limits, and other properties.

MapLonLimit — Geographic longitude limits of the display area

two-element vector

Geographic longitude limits of the display area, specified as a two-element vector of the form [western_limit eastern_limit]. This property can be set for many typical projections and geometries, but cannot be used with oblique projections or with globe, for example.

When applicable, the MapLonLimit property may affect the origin longitude if the Origin property is not set explicitly when calling axesm. It may also determine the value used for FLonLimit. See “Access and Change Map Axes Properties” for a more complete description of the applicability of MapLonLimit and its interaction with the origin, frame limits, and other properties.

Tips

- In general, after re-opening a saved figure that contains a map axes, you should not attempt to modify the projection properties of that map axes.
- When you create a map axes with axesm and right click in the axes, a context menu appears. If you do not need the menu or it interferes with your application, you can disable it by resetting the 'ButtonDownFcn' property of the axes:

```
ax = axesm('mercator');    % Right-clicking brings up context menu.
set(ax, 'ButtonDownFcn', []) % Context menu has been disabled.
```

See Also

Properties

Map Axes Properties

Functions

axes | gcm | getm | setm

Topics

“Introduction to Mapping Graphics”
 “The Map Axes”
 “The Map Frame”
 “Map Limit Properties”

“The Map Grid”

Introduced before R2006a

Map Axes Properties

Control axes appearance and behavior

Description

Map axes properties control the appearance and behavior of an `axesm` object. By changing property values, you can modify certain aspects of the map axes.

Properties

Properties That Control the Map Projection

AngleUnits — Angular unit of measure

'degrees' (default) | 'radians'

Angular unit of measure — Controls the units of measure used for angles (including latitudes and longitudes) in the map axes. All input data are assumed to be in the given units; 'degrees' is the default. For more information on angle units, see “Angle Representations and Angular Units” in the *Mapping Toolbox User's Guide*.

Aspect — Display aspect

'normal' (default) | 'transverse'

Display aspect — Controls the orientation of the base projection of the map. When the aspect is 'normal' (the default), *north* in the base projection is up. In a transverse aspect, north is to the right. A cylindrical projection of the whole world would look like a *landscape* display under a 'normal' aspect, and like a *portrait* under a 'transverse' aspect. Note that this property is not the same as projection aspect, which is controlled by the `Origin` property vector discussed later.

FalseEasting — Coordinate shift for projection calculations

0 (default) | numeric scalar

Coordinate shift for projection calculations — Modifies the position of the map within the axes. The projected coordinates are shifted in the *x*-direction by the amount of `FalseEasting`. The `FalseEasting` is in the same units as the projected coordinates,

that is, the units of the first element of the `Geoid` map axes property. False eastings and northings are sometimes used to ensure nonnegative values of the projected coordinates. For example, the Universal Transverse Mercator uses a false easting of 500,000 meters.

FalseNorthing — Coordinate shift for projection calculations

`0` (default) | numeric scalar

Coordinate shift for projection calculations — Modifies the position of the map within the axes. The projected coordinates are shifted in the *y*-direction by the amount of `FalseNorthing`. The `FalseNorthing` is in the same units as the projected coordinates, that is, the units of the first element of the `Geoid` map axes property. False eastings and northings are sometimes used to ensure nonnegative values of the projected coordinates. For example, the Universal Transverse Mercator uses a false northing of 0 in the northern hemisphere and 10,000,000 meters in the southern.

FixedOrient — Projection-based orientation

`[]` (default) | numeric scalar

This property is read-only.

Projection-based orientation — This read-only property fixes the orientation of certain projections (such as the Cassini and Wetch). When empty, which is true for most projections, the user can alter the orientation of the projection using the third element of the `Origin` property. When fixed, the fixed orientation is always used.

Geoid — Reference spheroid definition

`[1 0]` (default) | `referenceSphere` object | `referenceEllipsoid` object | `oblateSpheroid` object | `[semimajor_axis eccentricity]`

Reference spheroid definition — The spheroid (ellipsoid or sphere) for calculating the projections of any displayed map objects. It can be an `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a two-element vector of the form `[semimajor_axis eccentricity]`. The default value is an ellipsoid vector representing the unit sphere: `[1 0]`.

MapLatLimit — Geographic latitude limits of the display area

`[southern_limit northern_limit]`

Geographic latitude limits of the display area — Expressed as a two-element vector of the form `[southern_limit northern_limit]`. This property can be set for many typical projections and geometries, but cannot be used with oblique projections or with `globe`, for example. When applicable, the `MapLatLimit` property may affect the origin latitude if

the `Origin` property is not set explicitly when calling `axesm`. It may also determine the value used for `FFlatLimit`. See “Access and Change Map Axes Properties” for a more complete description of the applicability of `MapFlatLimit` and its interaction with the origin, frame limits, and other properties.

MapLonLimit — Geographic longitude limits of the display area

`[western_limit eastern_limit]`

Geographic longitude limits of the display area — Expressed as a two-element vector of the form `[western_limit eastern_limit]`. This property can be set for many typical projections and geometries, but cannot be used with oblique projections or with `globe`, for example. When applicable, the `MapLonLimit` property may affect the origin longitude if the `Origin` property is not set explicitly when calling `axesm`. It may also determine the value used for `FLonLimit`. See “Access and Change Map Axes Properties” for a more complete description of the applicability of `MapLonLimit` and its interaction with the origin, frame limits, and other properties.

MapParallels — Projection standard parallels

`[lat] | [lat1 lat2]`

Projection standard parallels — Sets the standard parallels of projection. It can be an empty, one-, or two-element vector, depending upon the projection. The elements are in the same units as the map axes `AngleUnits`. Many projections have specific, defining standard parallels. When a map axes object is based upon one of these projections, the parallels are set to the appropriate defaults. For conic projections, the default standard parallels are set to 15°N and 75°N, which biases the projection toward the northern hemisphere.

For projections with one defined standard parallel, setting the parallels to an empty vector forces recalculation of the parallel to the middle of the map latitude limits. For projections requiring two standard parallels, setting the parallels to an empty vector forces recalculation of the parallels to one-sixth the distance from the latitude limits (e.g., if the map latitude limits correspond to the northern hemisphere `[0 90]`, the standard parallels for a conic projection are set to `[15 75]`). For azimuthal projections, the `MapParallels` property always contains an empty vector and cannot be altered.

See the *Mapping Toolbox User's Guide* for more information on standard parallels.

MapProjection — Map projection

character vector

Map projection — Sets the projection, and hence all transformation calculations, for the map axes object. It is required in the creation of map axes. It must be a member of the recognized projection set, which you can list by typing `getm('MapProjection')` or `maps`. For more information on projections, see the *Mapping Toolbox User's Guide*. Some projections set their own defaults for other properties, such as parallels and trim limits.

Origin — Origin and orientation for projection calculations

[latitude longitude orientation]

Origin and orientation for projection calculations — Sets the map origin for all projection calculations. The latitude, longitude, and orientation should be in the map axes `AngleUnits`. Latitude and longitude refer to the coordinates of the map origin; orientation refers to an angle of skewness or rotation about the axis running through the origin point and the center of the earth. The default origin is 0° latitude and a longitude centered between the map longitude limits. If a scalar is entered, it is assumed to refer to the longitude; if a two-element vector is entered, the default orientation is 0°, a normal projection. If an empty origin vector is entered, the origin is centered on the map longitude limits. For more information on the origin, see the *Mapping Toolbox User's Guide*.

Parallels — Number of standard parallels

0 | 1 | 2

This property is read-only.

Number of standard parallels — This read-only property contains the number of standard parallels associated with the projection. See the *Mapping Toolbox User's Guide* for more information on standard parallels.

ScaleFactor — Scale factor for projection calculations

1 (default) | scalar

Scale factor for projection calculations — Modifies the size of the map in projected coordinates. The geographic coordinates are transformed to Cartesian coordinates by the map projection equations and multiplied by the scale factor. Scale factors are sometimes used to minimize the scale distortion in a map projection. For example, the Universal Transverse Mercator uses a scale factor of 0.996 to shift the line of zero scale distortion to two lines on either side of the central meridian.

Zone — Zone for certain projections

[] or 31N (default) | ZoneSpec

Zone for certain projections — Specifies the zone for certain projections. A zone is a region on the globe that has a special set of projection parameters. In the Universal Transverse Mercator Projection, the world is divided into quadrangles that are generally 6 degrees wide and 8 degrees tall. The number in the zone designation refers to the longitude range, while the letter refers to the latitude range. Most projections use the same parameters for the entire globe, and do not require a zone.

Properties That Control the Frame

Frame — Frame visibility

'off' (default) | 'on'

Frame visibility — Controls the visibility of the display frame box. When the frame is 'off' (the default), the frame is not displayed. When the frame is 'on', an enclosing frame is visible. The frame is a patch that is plotted as the lowest layer of displayed map objects. Regardless of its display status, the frame always operates in terms of trimming map data.

FFill — Frame plotting precision

100 (default) | scalar plotting point density

Frame plotting precision — Sets the number of points to be used in plotting the frame for display. The default value is 100, which for a rectangular frame results in a plot with 100 points for each side, or a total of 400 points. The number of points required for a reasonable display varies with the projection. Cylindrical projections such as the Miller require very few. Projections resulting in more complex frames, such as the Werner, look better with higher densities. The default value is generally sufficient.

FEdgeColor — Color of displayed frame edge

[0 0 0] (default) | ColorSpec

Color of the displayed frame edge — Specifies the color used for the displayed frame. You can specify a color using a vector of RGB values or a MATLAB colorSpec name. By default, the frame edge is displayed in black ([0 0 0]).

FFaceColor — Color of displayed frame face

'none' (default) | ColorSpec

Color of the displayed frame face — Specifies the color used for the displayed frame face. You can specify a color using a vector of RGB values or a MATLAB colorSpec name. By default, the frame face is 'none', meaning no face color is filled in. Another useful color is 'cyan' ([0 1 1]), which looks like water.

FLatLimit — Latitude limits of map frame relative to projection origin

[southern_limit northern_limit]

Latitude limits of map frame relative to projection origin — The map frame encloses the area in which data and graticule lines are plotted and beyond which they are trimmed. For non-oblique and non-azimuthal projections, which have quadrangular frames, this property controls the north-south extent of the frame. If a projection is made oblique by the inclusion of a non-zero rotation angle (the third element of the `Origin` vector), `FLatLimit` still applies, but in the rotated latitude-longitude system rather than in the geographic system. In the case of azimuthal projections, which have circular frames, `FLatLimit` takes the special form [-Inf radius] where radius is the spherical distance (in degrees or radians, depending on the `AngleUnits` property of the projection) from the projection origin to the edge of the frame.

Note In most common situations, including non-oblique cylindrical and conic projections and polar azimuthal projections, there is no need to set `FLatLimit`; use `MapLatLimit` instead.

FLineWidth — Frame edge line width

2 (default) | scalar

Frame edge line width — Sets the line width of the displayed frame edge. The value is a scalar representing points, which is 2 by default.

FLonLimit — Longitude limits of map frame relative to projection origin

[western_limit eastern_limit]

Longitude limits of map frame relative to projection origin — The map frame encloses the area in which data and graticule lines are plotted and beyond which they are trimmed. For non-oblique and non-azimuthal projections, which have quadrangular frames, this property controls the east-west extent of the frame. If a projection is made oblique by the inclusion of a non-zero rotation angle (the third element of the `Origin` vector), `FLonLimit` still applies, but in the rotated latitude-longitude system rather than in the geographic system. The `FLonLimit` property is ignored for azimuthal projections.

Note In most common situations, including non-oblique cylindrical and conic projections, there is no need to set `FLonLimit`; use `MapLonLimit` instead.

TrimLat — Bounds on FLatLimit

[southern_limit northern_limit]

This property is read-only.

Bounds on FLatLimit — This read-only property sets bounds on the values that `axesm` and `setm` will accept for the `MapLatLimit` and `FLatLimit` properties, which is necessary because some map projections cannot display the entire globe without extending to infinity. For example, `TrimLat` is `[-90 90]` degrees for most cylindrical projections and `[-86 86]` degrees for the Mercator projection because the north-south scale becomes infinite as one approaches either pole.

TrimLon — Bounds on FLonLimit

[western_limit eastern_limit]

This property is read-only.

Bounds on FLonLimit — This read-only property sets bounds on the values that `axesm` and `setm` will accept for the `MapLonLimit` and `FLonLimit` properties, which is necessary because some map projections cannot display the entire globe without extending to infinity. For example, `TrimLon` is `[-135 135]` degrees for most conic projections.

Properties That Control the Grid**Grid — Grid visibility**

'off' (default) | 'on'

Grid visibility — Controls the visibility of the display grid. When the grid is 'off' (the default), the grid is not displayed. When the grid is 'on', meridians and parallels are visible. The grid is plotted as a set of line objects.

GAltitude — Grid z-axis setting

Inf (default) | scalar

Grid z-axis setting — Sets the z-axis location for the grid when displayed. Its default value is infinity, which is displayed above all other map objects. However, you can set this to some other value for stacking objects above the grid, if desired.

GColor — Color of the displayed grid

[0 0 0] (default) | ColorSpec

Color of the displayed grid — Specifies the color used for the displayed grid. You can specify a color using a vector of RGB values or one of the MATLAB `colorSpec` names. By default, the map grid is displayed in black (`[0 0 0]`).

GLineStyle — Grid line style

: (default) | `LineStyle`

Grid line style — Determines the style of line used when the grid is displayed. You can specify any line style supported by the MATLAB `line` function. The default line style is a dotted line (that is, `' : '`).

GLineWidth — Grid line width

0.5 (default) | scalar

Grid line width — Sets the line width of the displayed grid. The value is a scalar representing points, which is 0.5 by default.

MLineException — Grid line width

[] (default) | vector

Exceptions to grid meridian limits — Allows specific meridians of the displayed grid to extend beyond the grid meridian limits to the poles. The value must be a vector of longitudes in the appropriate angle units. For longitudes so specified, grid lines extend from pole to pole regardless of the existence of any grid meridian limits. This vector is empty by default.

MLineFill — Grid meridian plotting precision

100 (default) | scalar plotting point density

Grid meridian plotting precision — Sets the number of points to be used in plotting the grid meridians. The default value is 100 points. The number of points required for a reasonable display varies with the projection. Cylindrical projections such as the Miller require very few. Projections resulting in more complex shapes, such as the Werner, look better with higher densities. The default value is generally sufficient.

MLineLimit — Grid meridian plotting precision

[] (default) | [`north south`] | [`south north`]

Grid meridian limits — Establishes latitudes beyond which displayed grid meridians do not extend. By default, this property is empty, so the meridians extend to the poles. There are two exceptions to the meridian limits. No meridian extends beyond the map latitude

limits, and exceptions to the meridian limits for selected meridians are allowed (see above).

MLineStyleLocation — Grid meridian interval or specific locations

30 (default) | scalar | vector

Grid meridian interval or specific locations — Establishes the interval between displayed grid meridians. When a scalar interval is entered in the map axes `MLineStyleLocation`, meridians are displayed, starting at 0° longitude and repeating every interval in both directions, which by default is 30°. Alternatively, you can enter a vector of longitudes, in which case a meridian is displayed for each element of the vector.

PLineException — Exceptions to grid parallel limits

[] (default) | vector

Exceptions to grid parallel limits — Allows specific parallels of the displayed grid to extend beyond the grid parallel limits to the International Date Line. The value must be a vector of latitudes in the appropriate angle units. For latitudes so specified, grid lines extend from the western to the eastern map limit, regardless of the existence of any grid parallel limits. This vector is empty by default.

PLineFill — Grid parallel plotting precision

100 (default) | scalar plotting point density

Grid parallel plotting precision — Sets the number of points to be used in plotting the grid parallels. The default value is 100. The number of points required for a reasonable display varies with the projection. Cylindrical projections such as the Miller require very few. Projections resulting in more complex shapes, such as the Bonne, look better with higher densities. The default value is generally sufficient.

PLineLimit — Grid parallel plotting precision

[] (default) | [east west] | [west east]

Grid parallel limits — Establishes longitudes beyond which displayed grid parallels do not extend. By default, this property is empty, so the parallels extend to the date line. There are two exceptions to the parallel limits. No parallel extends beyond the map longitude limits, and exceptions to the parallel limits for selected parallels are allowed (see above).

PLineLocation — Grid parallel interval or specific locations

15 (default) | scalar | vector

Grid parallel interval or specific locations — Establishes the interval between displayed grid parallels. When a scalar interval is entered in the map axes `PLineLocation`,

parallels are displayed, starting at 0° latitude and repeating every interval in both directions, which by default is 15°. Alternatively, you can enter a vector of latitudes, in which case a parallel is displayed for each element of the vector.

Properties That Control Grid Labeling

FontAngle — Select italic or normal font for all grid labels

'normal' (default) | 'italic' | 'oblique'

Select italic or normal font for all grid labels — Selects the character slant for all displayed grid labels. 'normal' specifies nonitalic font. 'italic' and 'oblique' specify italic font.

FontColor — Text color for all grid labels

'black' (default) | ColorSpec | 'oblique'

Text color for all grid labels — Sets the color of all displayed grid labels. ColorSpec is a three-element vector specifying an RGB triple or a predefined MATLAB color specification (colorSpec).

FontName — Font family name for all grid labels

'helvetica' (default) | 'courier' | 'symbol' | 'times'

Font family name for all grid labels — Sets the font for all displayed grid labels. To display and print properly, FontName must be a font that your system supports.

FontSize — Font size

0 (default) | scalar

Font size — An integer specifying the font size to use for all displayed grid labels, in units specified by the FontUnits property. The default point size is 9.

FontUnits — Units used to interpret the FontSize property

'points' (default) | 'normalized' | 'inches' | 'centimeters' | 'pixels'

Units used to interpret the FontSize property — When set to normalized, the toolbox interprets the value of FontSize as a fraction of the height of the axes. For example, a normalized FontSize of 0.1 sets the text characters to a font whose height is one-tenth of the axes' height. The default units ('points') are equal to 1/72 of an inch.

FontWeight — Select bold or normal font

'normal' (default) | 'bold'

Select bold or normal font — The character weight for all displayed grid labels.

LabelFormat — Labeling format for grid

'compass' (default) | 'signed' | 'none'

Labeling format for grid — Specifies the format of the grid labels. If 'compass' is employed (the default), meridian labels are suffixed with an “E” for east and a “W” for west, and parallel labels are suffixed with an “N” for north and an “S” for south. If 'signed' is used, meridian labels are prefixed with a “+” for east and a “-” for west, and parallel labels are suffixed with a “+” for north and a “-” for south. If 'none' is selected, straight latitude and longitude numerical values are employed, so western meridian labels and southern parallel labels will have a “-”, but no symbol precedes eastern and northern (positive) labels.

LabelRotation — Label Rotation

'off' (default) | 'on'

Label rotation — Determines whether the meridian and parallel labels are displayed without rotation (the default) or rotated to align to the graticule. This option is not available for the Globe display.

LabelUnits — Specify units and formatting for grid labels

'degrees' (default) | 'dm' | 'dms' | 'radians'

Specify units and formatting for grid labels — The display of meridian and parallel labels is controlled by the map axes LabelUnits property, as described in the following table.

| LabelUnits value | Label format |
|-------------------------|---------------------------------|
| 'degrees' | decimal degrees |
| 'dm' | degrees/decimal minutes |
| 'dms' | degrees/minutes/decimal seconds |
| 'radians' | decimal radians |

LabelUnits does not have a default of its own; instead it defaults to the value of AngleUnits at the time the map axes is constructed, which itself defaults to degrees. Although you can specify 'dm' and 'dms' for LabelUnits, these values are not accepted when setting AngleUnits.

MeridianLabel — Toggle display of meridian labels

'off' (default) | 'on'

Toggle display of meridian labels — Specifies whether the meridian labels are visible or not.

MLabelLocation — Specify meridians for labeling

scalar | vector

Specify meridians for labeling — Meridian labels need not coincide with the displayed meridian lines. Labels are displayed at intervals if a scalar in the map axes `MLabelLocation` is entered, starting at the prime meridian and repeating at every interval in both directions. If a vector of longitudes is entered, labels are displayed at those meridians. The default locations coincide with the displayed meridian lines, as specified in the `MLineStyleLocation` property.

MLabelParallel — Specify parallel for meridian label placement

'north' (default) | 'south' | 'equator' | scalar

Specify parallel for meridian label placement — Specifies the latitude location of the displayed meridian labels. If a scalar latitude is specified, all meridian labels are displayed at that latitude. If 'north' is specified, the maximum of the `MapLatLimit` is used; if 'south' is specified, the minimum of the `MapLatLimit` is used. If 'equator' is specified, a latitude of 0° is used.

MLabelRound — Specify significant digits for meridian labels

0 (default) | integer scalar

Specify significant digits for meridian labels — Specifies to which power of ten the displayed labels are rounded. For example, if `MLabelRound` is -1, labels are displayed down to the *tenths*. The default value of `MLabelRound` is 0; that is, displayed labels have no decimal places, being rounded to the *ones* column (10^0).

ParallelLabel — Toggle display of parallel labels

'off' (default) | 'on'

Toggle display of parallel labels — Specifies whether the parallel labels are visible or not.

PLabelLocation — Specify parallels for labeling

scalar | vector

Specify parallels for labeling — Parallel labels need not coincide with the displayed parallel lines. Labels are displayed at intervals if a scalar in the map axes `PLabelLocation` is entered, starting at the equator and repeating at every interval in both directions. If a vector of latitudes is entered, labels are displayed at those parallels.

The default locations coincide with the displayed parallel lines, as specified in the `PLineLocation` property.

PLabelMeridian — Specify meridian for parallel label placement

'west' (default) | 'east' | 'prime' | scalar

Specify meridian for parallel label placement — Specifies the longitude location of the displayed parallel labels. If a longitude is specified, all parallel labels are displayed at that longitude. If 'east' is specified, the maximum of the `MapLonLimit` is used; if 'west' is specified, the minimum of the `MapLonLimit` is used. If 'prime' is specified, a longitude of 0° is used.

PLabelRound — Specify significant digits for parallel labels

0 (default) | integer scalar

Specify significant digits for parallel labels — Specifies to which power of ten the displayed labels are rounded. For example, if `PLabelRound` is -1, labels are displayed down to the tenths. The default value of `PLabelRound` is 0; that is, displayed labels have no decimal places, being rounded to the ones column (10^0).

See Also

axes | axesm | gcm | getm | setm

Topics

“Introduction to Mapping Graphics”

“The Map Axes”

“The Map Frame”

“Map Limit Properties”

“The Map Grid”

Introduced before R2006a

axesscale

Resize axes for equivalent scale

Syntax

```
axesscale  
axesscale(hbase)  
axesscale(hbase, hother)
```

Description

`axesscale` resizes all axes in the current figure to have the same scale as the current axes (`gca`). In this context, scale means the relationship between axes x - and y -coordinates and figure and paper coordinates. When `axesscale` is used, a unit of length in x and y is printed and displayed at the same size in all the affected axes. The `XLimMode` and `YLimMode` of the axes are set to `'manual'` to prevent autoscaling from changing the scale.

`axesscale(hbase)` uses the axes `hbase` as the reference axes, and rescales the other axes in the current figure.

`axesscale(hbase, hother)` uses the axes `hbase` as the base axes, and rescales only the axes in `hother`.

Examples

Display Multiple Regions with a Common Scale

Display the conterminous United States, Alaska, and Hawaii in separate axes in the same figure, with a common scale.

Read state names and coordinates. Extract Alaska and Hawaii.

```
states = shaperead('usastatehi', 'UseGeoCoords', true);  
statenames = {states.Name};
```

```
alaska = states(strcmp('Alaska', statenames));  
hawaii = states(strcmp('Hawaii', statenames));
```


Create a figure for the conterminous states.

```
f = figure;  
hconus = usamap('conus');  
geoshow(states, 'FaceColor', [0.5 1 0.5]);  
load conus gtlakelat gtlakelon  
geoshow(gtlakelat, gtlakelon,...  
        'DisplayType', 'polygon', 'FaceColor', 'cyan')  
framem off; gridm off; mlabel off; plabel off
```




Display Alaska and Hawaii on different axes. For now, the axes overlap.

```
halaska = axes('Parent',f);  
usamap('alaska')  
geoshow(alaska, 'FaceColor', [0.5 1 0.5]);  
framem off; gridm off; mlabel off; plabel off  
  
hhawaii = axes('Parent',f);  
usamap('hawaii')  
geoshow(hawaii, 'FaceColor', [0.5 1 0.5]);  
framem off; gridm off; mlabel off; plabel off
```




Arrange the axes so they do not overlap. However, this changes the scale of the axes.


```
set(hconus, 'Position',[0.1 0.35 0.85 0.6])  
set(halaska, 'Position',[0.02 0.08 0.2 0.2])  
set(hhawaii, 'Position',[0.5 0.1 0.2 0.2])
```



Resize the Alaska and Hawaii axes based on the size of the conterminous United States.
axesscale(hconus)



Limitations

The equivalence of scales holds only as long as no commands are issued that can change the scale of one of the axes. For example, changing the units of the ellipsoid or the scale factor in one of the axes would change the scale.

Tips

To ensure the same map scale between axes, use the same ellipsoid and scale factors.

See Also

paperscale

Introduced before R2006a

azimuth

Azimuth between points on sphere or ellipsoid

Syntax

```
az = azimuth(lat1,lon1,lat2,lon2)
az = azimuth(lat1,lon1,lat2,lon2,ellipsoid)
az = azimuth(lat1,lon1,lat2,lon2,units)
az = azimuth(lat1,lon1,lat2,lon2,ellipsoid,units)
az = azimuth(track,...)
```

Description

`az = azimuth(lat1,lon1,lat2,lon2)` calculates the great circle azimuth from point 1 to point 2, for pairs of points on the surface of a sphere. The input latitudes and longitudes can be scalars or arrays of matching size. If you use a combination of scalar and array inputs, the scalar inputs will be automatically expanded to match the size of the arrays. The function measures azimuths clockwise from north and expresses them in degrees or radians.

`az = azimuth(lat1,lon1,lat2,lon2,ellipsoid)` computes the azimuth assuming that the points lie on the ellipsoid defined by the input `ellipsoid`. `ellipsoid` is a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. The default ellipsoid is a unit sphere.

`az = azimuth(lat1,lon1,lat2,lon2,units)` uses the input `units` to define the angle units of `az` and the latitude-longitude coordinates. Use `'degrees'` (the default value), in the range from 0 to 360, or `'radians'`, in the range from 0 to 2π .

`az = azimuth(lat1,lon1,lat2,lon2,ellipsoid,units)` specifies both the ellipsoid vector and the units of `az`.

`az = azimuth(track,...)` uses the input `track` to specify either a great circle or a rhumb line azimuth calculation. Enter `'gc'` for the `track` (the default value), to obtain great circle azimuths for a sphere or geodesic azimuths for an ellipsoid. (Hint to

remember name: the letters “g” and “c” are in both great circle and geodesic.) Enter 'rh' for the *track* to obtain rhumb line azimuths for either a sphere or an ellipsoid.

Examples

Find the azimuth between two points on the same parallel, for example, (10°N, 10°E) and (10°N, 40°E). The azimuth between two points depends on the *track* value selected.

```
% Try the 'gc' track value.
az = azimuth('gc',10,10,10,40)
```

```
% Compare to the result obtained from the 'rh' track value.
az = azimuth('rh',10,10,10,40)
```

Find the azimuth between two points on the same meridian, say (10°N, 10°E) and (40°N, 10°E):

```
% Try the 'gc' track .
az = azimuth(10,10,40,10)
```

```
% Compare to the 'rh' track .
az = azimuth('rh',10,10,40,10)
```

Rhumb lines and great circles coincide along meridians and the Equator. The azimuths are the same because the paths coincide.

Definitions

Azimuth

An *azimuth* is the angle at which a smooth curve crosses a meridian, taken clockwise from north. The North Pole has an azimuth of 0° from every other point on the globe. You can calculate azimuths for great circles or rhumb lines.

Geodesic

A *geodesic* is the shortest distance between two points on a curved surface, such as an ellipsoid.

Great Circle

A *great circle* is a type of geodesic that lies on a sphere. It is the intersection of the surface of a sphere with a plane passing through the center of the sphere. For great circles, the azimuth is calculated at the starting point of the great circle path, where it crosses the meridian. In general, the azimuth along a great circle is not constant. For more information, see “Great Circles”.

Rhumb Line

A *rhumb line* is a curve that crosses each meridian at the same angle. For rhumb lines, the azimuth is the *constant* angle between true north and the entire rhumb line passing through the two points. For more information, see “Rhumb Lines”.

Algorithms

Azimuths over Long Geodesics

Azimuth calculations for geodesics degrade slowly with increasing distance and can break down for points that are nearly antipodal or for points close to the Equator. In addition, for calculations on an ellipsoid, there is a small but finite input space. This space consists of pairs of locations in which both points are nearly antipodal *and* both points fall close to (but not precisely on) the Equator. In such cases, you will receive a warning and `az` will be set to NaN for the “problem pairs.”

Eccentricity

Geodesic azimuths on an ellipsoid are valid only for small eccentricities typical of the Earth (for example, 0.08 or less).

Alternatives

If you are calculating both the distance and the azimuth, you can call just the `distance` function. The function returns the azimuth as the second output argument. It is unnecessary to call `azimuth` separately.

See Also

distance | elevation | reckon | track | track1 | track2

Introduced before R2006a

boundImageSize

Bound size of raster map

Syntax

```
mapBound = boundImageSize(mapRequest, imageLength)
```

Description

`mapBound = boundImageSize(mapRequest, imageLength)` sets the bounds of the raster map `mapRequest` based on `imageLength`, the length in pixels for the row (`ImageHeight`) or column (`ImageWidth`) dimension.

Examples


Read and Display VMAP0 Basic Layer for Entire Globe

Read the VMAP0 basic layer for the entire globe.

```
vmap0 = wmsfind('vmap0.tiles', 'SearchField', 'serverurl');  
vmap0 = wmsupdate(vmap0);  
layer = refine(vmap0, 'basic');  
request = WMSMapRequest(layer);  
request.Transparent = true;  
imageLength = 720;  
request = boundImageSize(request, imageLength);  
globalImage = getMap(request.Server, request.RequestURL);
```

Display the map. The rendered map has a spatial resolution of 0.5 degrees per cell and an image size of 360-by-720 pixels.

```
figure; worldmap('world')  
geoshow(globalImage, request.RasterReference);  
title(['VMAP0 ' layer.LayerTitle ' Layer'])
```

Courtesy Metacarta

Read and Display Multiple Layers Centered Around London

Read and display multiple layers centered around London. The rendered map has a spatial extent of 0.5 degrees and an image size of 1024-by-1024 pixels

```

vmap0 = wmsfind('vmap0.tiles', 'SearchField', 'serverurl');
vmap0 = wmsupdate(vmap0);
layers = [ refine(vmap0, 'rail'); refine(vmap0, 'river'); ...
           refine(vmap0, 'priroad'); refine(vmap0, 'secroad'); ...
           refine(vmap0, 'ctylabel'); refine(vmap0, 'basic')];
request = WMSMapRequest(layers);
cities = shaperead('worldcities', 'UseGeo', true);
london = cities(strncmp('London', {cities.Name}));
extent = [-.25 .25];
request.Latlim = london.Lat + extent;
request.Lonlim = london.Lon + extent;


request.Transparent = true;
imageLength = 1024;
request = boundImageSize(request, imageLength);
londonImage = getMap(request.Server, request.RequestURL);

```

Display the map. The rendered map has a spatial extent of 0.5 degrees and an image size of 1024-by-1024 pixels

```
figure
worldmap(londonImage,request.RasterReference)
geoshow(londonImage,request.RasterReference)
title({'Region Surrounding London, England', ...
      ['with Primary and Secondary Roads, ', ...
      'Rivers, Rails, City Label, and Basic Layers']})
```

Region Surrounding London, England
with Primary and Secondary Roads, Rivers, Rails, City Label, and Basic Layers



Original Web map service map, specified as a `WMSMapRequest` object.

imageLength — Row or column length of input WMS map

positive scalar

Row or column length of input WMS map, specified as a positive scalar. `imageLength` indicates the length in pixels for the row (`ImageHeight`) or column (`ImageWidth`) dimension.

Example: 720

Data Types: `double`

Output Arguments

mapBound — Bound Web map service map

`WMSMapRequest` object

Bound Web map service map, returned as a `WMSMapRequest` object.

Algorithms

The `boundImageSize` function calculates the row or column dimension length by using the aspect ratio of the `LatLim` and `LonLim` properties or the aspect ratio of the `XLim` and `YLim` properties of `mapBound`, if they are set.

`boundImageSize` measures image dimensions in geographic or map coordinates. The function sets the longest image dimension to `imageLength`, and the shortest to the nearest integer value that preserves the aspect ratio, without changing the coordinate limits. The maximum value of the `MaximumHeight` and `MaximumWidth` properties becomes the maximum value of `imageLength`.

See Also

Introduced in R2009b

bufferm

Buffer zones for latitude-longitude polygons

Syntax

```
[latb,lonb] = bufferm(lat,lon,bufwidth)
[latb,lonb] = bufferm(lat,lon,bufwidth,direction)
[latb,lonb] = bufferm(lat,lon,bufwidth,direction,npts)
```

Description

[latb,lonb] = bufferm(lat,lon,bufwidth) computes the buffer zone around a line or polygon. If the vectors `lat` and `lon`, in units of degrees, define a line, then `latb` and `lonb` define a polygon that contains all the points that fall within a certain distance, `bufwidth`, of the line. `bufwidth` is a scalar specified in degrees of arc along the surface. If the vectors `lat` and `lon` define a polygon, then `latb` and `lonb` define a region that contains all the points exterior to the polygon that fall within `bufwidth` of the polygon.

[latb,lonb] = bufferm(lat,lon,bufwidth,direction) where `direction` specifies whether the buffer zone is inside ('in') or outside ('out') of the polygon. A third option, 'outPlusInterior', returns the union of an exterior buffer (as would be computed using 'out') with the interior of the polygon. If you do not supply a `direction` value, `bufferm` uses 'out' as the default and returns a buffer zone outside the polygon. If you supply 'in' as the `direction` value, `bufferm` returns a buffer zone inside the polygon. If you are finding the buffer zone around a line, 'out' is the only valid option.


[latb,lonb] = bufferm(lat,lon,bufwidth,direction,npts) controls the number of points used to construct circles about the vertices of the polygon. A larger number of points produces smoother buffers, but requires more time. If `npts` is omitted, 13 points per circle are used.

Examples

Display Buffer Zones Inside and Outside the Great Lakes


Display a simplified version of the five polygons that represent the Great Lakes.

```
load conus
tol = 0.05;
[latr, lonr] = reducem(gtlakelat, gtlakelon, tol);
figure('Color','w')
ax = usamap({'MN','NY'});
setm(ax,'MLabelLocation',5)
geoshow(latr, lonr, 'DisplayType', 'polygon', ...
        'FaceColor', 'blue')
title('Great Lakes')
```




Set the buffer width and display a buffer zone outside the lakes.

```
figure;  
bufwidth = 1;  
[latb, lonb] = bufferm(latr, lonr, bufwidth);  
geoshow(latb, lonb, 'DisplayType', 'polygon', ...  
        'FaceColor', 'yellow')  
title('Exterior Buffer Zone')
```




Display a buffer zone inside the polygon.

```
figure;  
[lati, loni] = bufferm(latr, lonr, 0.3*bufwidth, 'in');  
geoshow(lati, loni, 'DisplayType', 'polygon', ...  
        'FaceColor', 'magenta')  
title('Interior Buffer Zone')
```


Display the Great Lakes with interior and exterior buffer zones on a backdrop of neighboring states.

```
figure('Color','w')
ax = usamap({'MN','NY'});
setm(ax,'MLabelLocation',5)
geoshow(latb, lonb, 'DisplayType', 'polygon', 'FaceColor', 'yellow')
geoshow(latr, lonr, 'DisplayType', 'polygon', 'FaceColor', 'blue')
geoshow(lati, loni, 'DisplayType', 'polygon', 'FaceColor', 'magenta')
geoshow(uslat, uslon)
geoshow(statelat, statelon)
title('Great Lakes and Buffer Zones with Neighboring States')
```



Use the 'outPlusInterior' option.

```
bufWidth = 0.5;  
[latz, lonz] = bufferm(latr, lonr, bufWidth, 'outPlusInterior');  
figure  
geoshow(latz, lonz, 'DisplayType', 'polygon', 'FaceColor', 'yellow')  
title('Exterior Buffer Zone including Polygon Interior');
```



Tips

Close all polygons before processing them with `bufferm`. If a polygon is not closed, `bufferm` assumes it is a line.

See Also

`polyshape`

Introduced before R2006a

bufgeoquad

Expand limits of geographic quadrangle

Syntax

```
[latlim,lonlim] = bufgeoquad(latlim,lonlim,buflat,buflon)
```

Description

[latlim,lonlim] = bufgeoquad(latlim,lonlim,buflat,buflon) returns an expanded version of the geographic quadrangle defined by latlim and lonlim.

Examples

Bounding Quadrangle for U.S.

Bounding quadrangle for the Conterminous United States, buffered 2 degrees to the north and south and 3 degrees to the east and west.

Load data and expand the limits of the quadrangle.

```
conus = load('conus.mat');  
[latlim, lonlim] = geoquadline(conus.uslat,conus.uslon);  
[latlim,lonlim] = bufgeoquad(latlim,lonlim,2,3)
```

```
latlim =
```

```
    23.1200    51.3800
```

```
lonlim =
```

-127.7200 -63.9700

Input Arguments

latlim — Latitude limits

1-by-2 vector

Latitude limits of a geographic quadrangle, specified as a 1-by-2 vector of the form [southern_limit northern_limit], with latitudes in degrees. The two elements must be in ascending order, and lie in the closed interval [-90 90].

Data Types: single | double

lonlim — Longitude limits

1-by-2 vector

Longitude limits of a geographic quadrangle, specified as a 1-by-2 vector of the form [western_limit eastern_limit], with longitudes in degrees. The two limits need not be in numerical ascending order.

Data Types: single | double

buflat — Latitude buffer size

nonnegative scalar

Latitude buffer size, specified as a nonnegative scalar, in units of degrees.

Data Types: double

buflon — Longitude buffer size

nonnegative scalar

Longitude buffer size, specified as a nonnegative scalar, in units of degrees.

Data Types: double

Output Arguments

latlim — Latitude limits

1-by-2 vector

Latitude limits of a geographic quadrangle, returned as a 1-by-2 vector of the form `[southern_limit northern_limit]`, in units of degrees. The elements are in ascending order, and both lie in the closed interval `[-90 90]`.

lonlim — Longitude limits

1-by-2 vector

Longitude limits of a geographic quadrangle, returned as a 1-by-2 vector of the form `[western_limit eastern_limit]`, in units of degrees. The limits are wrapped to the interval `[-180 180]`. They are not necessarily in numerical ascending order.

See Also

`geoquadline` | `geoquadpt` | `outlinegeoquad`

Introduced in R2012b

camposm

Set camera position using geographic coordinates

Syntax

```
camposm(lat, long, alt)
[x, y, z] = camposm(lat, long, alt)
```

Description

`camposm(lat, long, alt)` sets the axes `CameraPosition` property of the current map axes to the position specified in geographic coordinates. The inputs `lat` and `long` are assumed to be in the angle units of the current map axes.

`[x, y, z] = camposm(lat, long, alt)` returns the camera position in the projected Cartesian coordinate system.


Examples

Look at northern Australia from a point south and one Earth radius above New Zealand:

```
figure
axesm('globe', 'galt', 0)
gridm('glinestyle', '-')
load topo
geoshow(topo, topolegend, 'DisplayType', 'texturemap');
demcmap(topo)
camlight;
material(0.6*[ 1 1 1])
plat = -50; plon = 160;
tlat = -10; tlon = 130;
camtargm(tlat, tlon, 0);
camposm(plat, plon, 1);
camupm(tlat, tlon)
set(gca, 'CameraViewAngle', 75)
land = shaperead('landareas.shp', 'UseGeoCoords', true)
```



```
linem([land.Lat],[land.Lon])  
axis off
```



See Also

[campos](#) | [camtargm](#) | [camupm](#) | [camva](#)

Introduced before R2006a

camtargm

Set camera target using geographic coordinates

Syntax

```
camtargm(lat, long, alt)
[x, y, z] = camtargm(lat, long, alt)
```

Description

`camtargm(lat, long, alt)` sets the axes `CameraTarget` property of the current map axes to the position specified in geographic coordinates. The inputs `lat` and `long` are assumed to be in the angle units of the current map axes.


`[x, y, z] = camtargm(lat, long, alt)` returns the camera target in the projected Cartesian coordinate system.

Examples

Look down the spine of the Andes from a location three Earth radii above the surface:

```
figure
axesm('globe', 'galt', 0)
gridm('glinestyle', '- ')
load topo
geoshow(topo, topolegend, 'DisplayType', 'texturemap');
demcmmap(topo)
lightm(-80, -180);
material(0.6*[ 1 1 1])
plat = 10; plon = -65;
tlat = -30; tlon = -70;
camtargm(tlat, tlon, 0);
camposm(plat, plon, 3);
camupm(tlat, tlon);
camva(20)
set(gca, 'CameraViewAngle', 30)
```

```
land = shaperead('landareas.shp','UseGeoCoords',true)
linem([land.Lat],[land.Lon])
axis off
```



See Also

[camposm](#) | [camtarget](#) | [camupm](#) | [camva](#)

Introduced before R2006a

camupm

Set camera up vector using geographic coordinates

Syntax

```
camupm(lat, long)
[x, y, z] = camupm(lat, long)
```

Description

`camupm(lat, long)` sets the axes `CameraUpVector` property of the current map axes to the position specified in geographic coordinates. The inputs `lat` and `long` are assumed to be in the angle units of the current map axes.


`[x, y, z] = camupm(lat, long)` returns the camera position in the projected Cartesian coordinate system.

Examples

Look at northern Australia from a point south of and one Earth radius above New Zealand. Set `CameraUpVector` to the antipode of the camera target for that *down under* view:

```
figure
axesm('globe', 'galt', 0)
gridm('glinestyle', '- ')
load topo
geoshow(topo, topolegend, 'DisplayType', 'texturemap');
demcmap(topo)
camlight;
material(0.6*[ 1 1 1])
plat = -50; plon = 160;
tlat = -10; tlon = 130;
[alat, alon] = antipode(tlat, tlon);
camtargm(tlat, tlon, 0);
```

```
camposm(plat,plon,1);  
camupm(alat,alon)  
set(gca,'CameraViewAngle',80)  
land = shaperead('landareas.shp','UseGeoCoords',true)  
linem([land.Lat],[land.Lon])  
axis off
```



See Also

[camposm](#) | [camtargm](#) | [camup](#) | [camva](#)

Introduced before R2006a

cart2grn

Transform projected coordinates to Greenwich system

Syntax

```
[lat,lon,alt] = cart2grn  
[lat,lon,alt] = cart2grn(hndl)  
[lat,lon,alt] = cart2grn(hndl,mstruct)
```

Description

When objects are projected and displayed on map axes, they are plotted in Cartesian coordinates appropriate for the selected projection. This function transforms those coordinates back into the Greenwich frame, in which longitude is measured positively East from Greenwich (longitude 0), England and negatively West from Greenwich.

`[lat,lon,alt] = cart2grn` returns the latitude, longitude, and altitude data in geographic coordinates of the current map object, removing any clips or trims introduced during the display process from the output data.

`[lat,lon,alt] = cart2grn(hndl)` specifies the displayed map object desired with its handle `hndl`. The default handle is `gco`.

`[lat,lon,alt] = cart2grn(hndl,mstruct)` specifies the map structure associated with the object. The map structure of the current axes is the default.

See Also

`gcm` | `mfwdtran` | `minvtran` | `project`

Introduced before R2006a

cat

Concatenate geographic or planar vector

Syntax

```
v = cat(1,v1,v2,...)
```

Description

`v = cat(1,v1,v2,...)` concatenates the geographic or planar vectors `v1,v2`, and so on, along the first dimension. If the class type of any property is a cell array, then the resultant field in the output `v` is also a cell array.

Examples

Concatenate Two Geopoint Vectors

Create two geopoint vectors. The first vector has one feature, and the second vector has two features. The vectors have different dynamic properties.

```
gp1 = geopoint(52,-101, 'Weather', 'Cloudy');  
gp2 = geopoint([42 42.2], [-110.5 -110.7], 'Temperature', [65.6 63.2]);
```

Concatenate the vectors into a single geopoint vector. Note that the first input argument must be 1.

```
p = cat(1,gp1,gp2)
```

```
p =  
3x1 geopoint vector with properties:
```

```
Collection properties:  
    Geometry: 'point'  
    Metadata: [1x1 struct]  
Feature properties:
```

```
Latitude: [52 42 42.2000]
Longitude: [-101 -110.5000 -110.7000]
Weather: {'Cloudy' '' ''}
Temperature: [0 65.6000 63.2000]
```

The concatenated vector has three features, and all features have all dynamic properties. Default property values are used when the value was not specified in the original geopoint vector. For example, the 'Temperature' value of the first feature is set to 0 since no 'Temperature' value was specified in gp1.

Input Arguments

v1, v2, ... — Geographic or planar vectors to be concatenated

geopoint, geoshape, mappoint, or mapshape objects

Geographic or planar vectors to be concatenated, specified as geopoint, geoshape, mappoint, or mapshape objects. All of v1, v2, ... are the same type of object.

Output Arguments

v — Concatenated geographic or planar vector

geopoint, geoshape, mappoint, or mapshape object

Concatenated geographic or planar vector, returned as a geopoint, geoshape, mappoint, or mapshape object. The object type of v matches the object type of v1, v2, ...

See Also

vertcat

Introduced in R2012a

changem

Substitute values in data array

Syntax

```
mapout = changem(Z, newcode, oldcode)
```

Description

`mapout = changem(Z, newcode, oldcode)` returns a data grid `mapout` identical to the input data grid, except that each element of `Z` with a value contained in the vector `oldcode` is replaced by the corresponding element of the vector `newcode`.

`oldcode` is 0 (scalar) by default, in which case `newcode` must be scalar. Otherwise, `newcode` and `oldcode` must be the same size.

Examples

Invent a map:

```
A = magic(3)
```

```
A =  
    8     1     6  
    3     5     7  
    4     9     2
```

Replace instances of 8 or 9 with 0s:

```
B = changem(A, [0 0], [9 8])
```

```
B =  
    0     1     6  
    3     5     7  
    4     0     2
```

Introduced before R2006a

circcirc

Intersections of circles in Cartesian plane

Syntax

```
[xout,yout] = circcirc(x1,y1,r1,x2,y2,r2)
```

Description

`[xout,yout] = circcirc(x1,y1,r1,x2,y2,r2)` finds the points of intersection (if any), given two circles, each defined by center and radius in x - y coordinates. In general, two points are returned. When the circles do not intersect or are identical, `NaNs` are returned.

When the two circles are tangent, two identical points are returned. All inputs must be scalars.

See Also

`linecirc`

Introduced before R2006a

clabelm

Add contour labels to map contour display

Syntax

```
clabelm(C)
clabelm(C,h)
clabelm(C,v)
clabelm(C,h,v)
clabelm( ____,Name,Value)

clabelm(C,'manual')
clabelm(C,h,'manual')

text_handles = clabel( ____)
```

Description

`clabelm(C)` labels all contours displayed in the current contour plot. Labels are upright and displayed with '+' symbols. `clabelm` randomly selects label positions.

`clabelm(C,h)` rotates the labels and inserts them in the contour lines. This syntax inserts only those labels that fit within the contour, depending on the size of the contour.

`clabelm(C,v)` labels only the contour levels specified by the vector, `v`.

`clabelm(C,h,v)` labels only the contour levels specified by vector `v`, rotates the labels, and inserts them in the contour lines.

`clabelm(____,Name,Value)` specifies the text object properties and the 'LabelSpacing' contourgroup property, using one or more `Name, Value` pair arguments, in addition to any of the input arguments in previous syntaxes.

`clabelm(C,'manual')` places contour labels at locations you select with a mouse. Click the mouse or press the space bar to label the contour closest to the center of the crosshair. Press the **Return** key while the cursor is within the figure window to terminate labeling.

`clabelm(C,h,'manual')` places contour labels at locations you select with a mouse. Press the **Return** key while the cursor is within the figure window to terminate labeling. The labels are rotated and inserted in the contour lines.

`text_handles = clabel(____)` additionally returns an array containing the handles of the text objects created, using any of the input arguments in the previous syntaxes. If you call `clabel` without the `h` argument, `text_handles` also contains the handles of line objects used to create the '+' symbols.

Input Arguments

C — Contour matrix

2-by-n matrix

Contour matrix containing the data that defines the contour lines. `C` is returned by the `contourm`, `contourfm`, or `contour3m` functions.

h — Handle to the `contourgroup` object

Handle to the `contourgroup` object returned by the `contourm`, `contourfm`, or `contour3m` functions.

v — Contour level values

vector

Contour level values, specified as a row or column vector of individual values.

Example: `[0,10,20]`

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1,Value1,...,NameN,ValueN`.

LabelSpacing — Spacing between labels

144 (default) | scalar

Spacing between labels on each contour line, specified as the comma-separated pair consisting of 'LabelSpacing' and a scalar. Specify the label spacing in points, where 1 point = $1/72$ inch.

Example: 'LabelSpacing',72

Output Arguments

text_handles — Handles of text objects

Handles of the text objects that `clabelm` creates. The `UserData` properties of the text objects contain the contour values displayed.


If you call `clabelm` without the `h` argument, `text_handles` also contains the handles of line objects used to create the '+' symbols.

Examples

Add Labels to a Contour Map

Generate a contour map and obtain the contour matrix, `C`, and the handle to the `contourgroup` object, `h`. Then display labels on the contour map.

```
load geoid
axesm miller
framem
tightmap
[C,h] = contourm(geoid,geoidlegend,-100:50:80);
clabelm(C,h)
```



See Also

[clabel](#) | [clegendm](#) | [contour3m](#) | [contourfm](#) | [contourm](#)

Introduced before R2006a

clegendm

Add legend labels to map contour display

Syntax

```
clegendm(C,h)
clegendm(C,h,loc)
clegendm( ____,unitstr)
clegendm( ____,labels)
hl = clegendm( ____ )
```

Description

`clegendm(C,h)` adds a legend specifying the contour line heights, `C`, to the current map contour plot, `h`.

`clegendm(C,h,loc)` places the legend in a specified location.

`clegendm(____,unitstr)` appends a string `unitstr` to each entry in the legend.

`clegendm(____,labels)` uses the text specified in `labels` to label the legend.

`hl = clegendm(____)` returns the handle to the legend object created.

Examples


Create Legend for Contour Display

Create a legend in the lower right-hand corner, specifying the contour elevations are in meters.

```
load topo
R = georasterref('RasterSize',size(topo), ...
    'Latlim',[-90 90],'Lonlim',[0 360]);
```



```
figure('Color','w');
worldmap('world')
[c,h] = contourm(topo,R,6000:1500:6000);
clegendm(c,h,4,'m')
```



Input Arguments

C — Contour matrix

numeric matrix

Contour matrix, specified as a matrix with two rows. The first row represents longitude data and the second row represents latitude data. You can create a contour matrix by using `contourm`, `contour3m`, or `contourfm`.

h — Handle of contour patches

hggroup

Handle to the contour patches drawn onto the current axes, returned as an hggroup. You can get a handle to contour patches by using `contourm`, `contour3m`, or `contourfm`.

loc — Location

0 (default) | 1 | 2 | 3 | 4 | -1

Location to place legend, specified as one of the following integers.

| Value | Placement |
|-------|-------------------------------|
| 0 | Automatic placement (default) |
| 1 | Upper right corner |
| 2 | Upper left corner |
| 3 | Lower left corner |
| 4 | Lower right corner |
| -1 | To the right of the plot |

unitstr — Text to append

character vector | string scalar

Text to append to each entry in the legend, specified as a character vector or string scalar.

labels — Labels

cell array of character vectors | string array

Labels in the legend, specified as a string array or cell array of character vectors. `labels` must have the same number of entries as the line children of `h`.

Output Arguments

h1 — Handle to legend object

handle

Handle to legend object created by the `clegendm` function, returned as a handle.

See Also

clabelm | contour3m | contourc | contourcbar | contourfm | contourm

Introduced before R2006a

clipdata

Clip data at $\pm\pi$ in longitude, $\pm\pi$ in latitude

Syntax

```
[lat,long,splitpts] = clipdata(lat,long,object)
```

Description

`[lat,long,splitpts] = clipdata(lat,long,object)` inserts NaNs at the appropriate locations in a map object so that a displayed map is clipped at the appropriate edges. It assumes that the clipping occurs at $\pm\pi/2$ radians in the latitude (y) direction and $\pm\pi$ radians in the longitude (x) direction.

The input data must be in radians and properly transformed for the particular aspect and origin so that it fits in the specified clipping range.

The output data is in radians, with NaNs placed at the proper locations. The output variable `splitpts` returns the row and column indices of the clipped elements (columns 1 and 2 respectively). These indices are necessary to restore the original data if the map parameters or projection are ever changed.

The `object` parameter can have any of the following values:

| Object to clip | Description |
|----------------|------------------------------|
| 'surface' | graticules |
| 'light' | lights |
| 'line' | lines |
| 'patch' | patches |
| 'text' | text object location points |
| 'point' | point data |
| 'none' | skip all clipping operations |

See Also

trimdata | undoclip | undotrim

Introduced before R2006a

clma

Clear current map axes

Syntax

```
clma  
clma all  
clma purge
```

Description

`clma` deletes all displayed map objects from the current map axes but leaves the frame if it is displayed.

`clma all` deletes all displayed map objects, including the frame, but it leaves the map structure intact, thereby retaining the map axes.

`clma purge` removes the map definition from the current axes, but leaves all objects projected on the axes intact.

See Also

`cla` | `clmo` | `handlem` | `hidem` | `namem` | `showm` | `tagm`

Introduced before R2006a

clmo

Clear specified graphics objects from map axes

Syntax

```
clmo  
clmo(handle)  
clmo(object)
```

Description

`clmo` deletes all displayed graphics objects on the current axes.

`clmo(handle)` deletes those objects specified by their handles.

`clmo(object)` deletes those objects with names identical to the value `object`. This can be any value recognized by the `handlem` function, including entries in the `Tag` property of each object, or the object `Type` if the `Tag` property is empty.

See Also

`clma` | `handlem` | `hidem` | `namem` | `showm` | `tagm`

Introduced before R2006a

closePolygonParts

Close all rings in multipart polygon

Syntax

```
[xdata, ydata] = closePolygonParts(xdata, ydata)
[lat, lon] = closePolygonParts(lat, lon, angleunits)
```

Description

`[xdata, ydata] = closePolygonParts(xdata, ydata)` ensures that each ring in a multipart (NaN-separated) polygon is “closed” by repeating the start point at the end of each ring, unless the start and end points are already identical. Coordinate vectors `xdata` and `ydata` must match in size and have identical NaN locations.

`[lat, lon] = closePolygonParts(lat, lon, angleunits)` works with latitude-longitude data and accounts for longitude wrapping with a period of 360 if `angleunits` is 'degrees' and 2π if `angleunits` is 'radians'. For a ring to be considered closed, the latitudes of its first and last vertices must match exactly, but their longitudes need only match modulo the appropriate period. Such rings are returned unaltered.

Examples

Close Polygon in Plane Coordinates

Create two vectors of planar coordinates.

```
xOpen = [1 0 2 NaN 0.5 0.5 1 1];
yOpen = [0 1 2 NaN 0.8 1 1 0.8];
```

Create a closed polygon from these coordinates.

```
[xClosed, yClosed] = closePolygonParts(xOpen, yOpen)
```



```

xClosed = 1x10
    1.0000    0    2.0000    1.0000    NaN    0.5000    0.5000    1.0000    1.0000    1.0000

yClosed = 1x10
    0    1.0000    2.0000    0    NaN    0.8000    1.0000    1.0000    1.0000    0.8000

```

Display all variables.

```
whos
```

| Name | Size | Bytes | Class | Attributes |
|---------|------|-------|--------|------------|
| xClosed | 1x10 | 80 | double | |
| xOpen | 1x8 | 64 | double | |
| yClosed | 1x10 | 80 | double | |
| yOpen | 1x8 | 64 | double | |

Close Polygon in Latitude-Longitude Coordinates

Load coastline data from MAT-file.

```
load coastlines
```

Construct a two-part polygon based on the coastlines data. The first ring is Antarctica. The longitude of its first vertex is -180 and the longitude of its last vertex is 180. The second ring is a small island from which the last vertex, a replica of the first vertex, is removed.

```

[latparts, lonparts] = polysplit(coastlat, coastlon);
latparts{2}(end) = [];
lonparts{2}(end) = [];
latparts(3:end) = [];
lonparts(3:end) = [];
[lat, lon] = polyjoin(latparts, lonparts);

```

Examine how `closePolygonParts` treats the two rings. In both cases, the first and last vertices differ. However, Antarctica remains unchanged while the small island is closed back up.

```
[latClosed, lonClosed] = closePolygonParts(lat, lon, 'degrees');  
[latpartsClosed, lonpartsClosed] = polysplit(latClosed, lonClosed);  
lonpartsClosed{1}(end) - lonpartsClosed{1}(1) % Result is 360  
  
ans = 360  
  
lonpartsClosed{2}(end) - lonpartsClosed{2}(1) % Result is 0  
  
ans = 0
```

See Also

[isshapemultipart](#) | [removeextrananseseparators](#)

Introduced in R2006a

colorui

Interactively define RGB color

Note colorui will be removed in a future release. Use `uicolor` instead.

Syntax

```
c = colorui
c = colorui(InitClr)
c = colorui(InitClr, FigTitle)
```

Description

`c = colorui` creates an interface for the definition of an RGB color triplet. On Windows® platforms, `colorui` produces the same interface as `uicolor`. On other machines, `colorui` produces a platform-independent dialog for specifying the color values.

`c = colorui(InitClr)` initializes the color value to the RGB triple given in `initclr`.

`c = colorui(InitClr, FigTitle)` where the character vector `FigTitle` specifies the window label.

The output value `c` is the selected RGB triple if the **Accept** or **OK** button is pushed. If the user presses **Cancel**, then the output value is set to `0`.

See Also

`uicolor`

combntns

All possible combinations of set of values

Note `combntns` will be removed in a future release. Use `nchoosek` instead.

Syntax

```
combos = combntns(set,subset)
```

Description

`combos = combntns(set,subset)` returns a matrix whose rows are the various combinations that can be taken of the elements of the vector `set` of length `subset`. Many combinatorial applications can make use of a vector `1:n` for the input `set` to return generalized, indexed combination subsets.

The `combntns` function provides the combinatorial subsets of a set of numbers. It is similar to the mathematical expression *a choose b*, except that instead of the number of such combinations, the actual combinations are returned. In combinatorial counting, the ordering of the values is not significant.

The numerical value of the mathematical statement *a choose b* is `size(combos,1)`.

Examples

How can the numbers 1 to 5 be taken in sets of three (that is, what is *5 choose 3*)?

```
combos = combntns(1:5,3)
```

```
combos =  
    1     2     3  
    1     2     4  
    1     2     5  
    1     3     4
```

```
1 3 5
1 4 5
2 3 4
2 3 5
2 4 5
3 4 5
size(combos,1) % "5 choose 3"

ans =
    10
```

Note that if a value is repeated in the input vector, each occurrence is treated as independent:

```
combos = combtnts([2 2 5],2)

combos =
    2    2
    2    5
    2    5
```

Tips

This is a recursive function.

Introduced before R2006a

comet3m

Project 3-D comet plot on map axes

Note comet3m will be removed in a future release. Use the following instead:

```
[x,y,z] = mfdtran(lat,lon,z);  
comet3(x,y,z,p)
```

Syntax

```
comet3m(lat,lon,z)  
comet3m(lat,lon,z,p)
```

Description

comet3m(lat,lon,z) traces a comet plot through the points specified by the input latitude, longitude, and altitude vectors.

comet3m(lat,lon,z,p) specifies a comet body of length p*length(lat). The input p is 0.1 by default.

A comet plot is an animated graph in which a circle (the comet *head*) traces the data points on the screen. The comet *body* is a trailing segment that follows the head. The *tail* is a solid line that traces the entire function.

Examples

Create a 3-D comet plot of the coastlines data:

```
load coastlines  
z = (1:length(coastlat))'/3000;  
axesm miller  
framem; gridm;  
setm(gca,'galtitude',max(z)+.5)
```

```
view(3)  
comet3m(coastlat,coastlon,z,0.01)
```

See Also

comet3 | cometm

Introduced before R2006a

cometm

Project 2-D comet plot on map axes

Note cometm will be removed in a future release. Use the following instead:

```
[x,y] = mfwdtran(lat,lon);  
comet(x,y,p)
```

Syntax

```
cometm(lat,lon)  
cometm(lat,lon,p)
```

Description

cometm(lat,lon) traces a comet plot through the points specified by the input latitude and longitude vectors.

cometm(lat,lon,p) specifies a comet body of length p*length(lat). The input p is 0.1 by default.

A comet plot is an animated graph in which a circle (the comet *head*) traces the data points on the screen. The comet *body* is a trailing segment that follows the head. The *tail* is a solid line that traces the entire function.

Examples

Create a comet plot of the coastlines data:

```
load coastlines  
axesm miller  
framem  
cometm(coastlat,coastlon,0.01)
```


See Also

comet | comet3m

Introduced before R2006a

map.geodesy.ConformalLatitudeConverter

Convert between geodetic and conformal latitudes

Description

A `ConformalLatitudeConverter` object provides conversion methods between geodetic and conformal latitudes for an ellipsoid with a given eccentricity.

The conformal latitude maps an ellipsoid (oblate spheroid) to a sphere while preserving shapes and angles locally. (Curves that meet at a given angle on the ellipsoid meet at the same angle on the sphere.) Use conformal latitudes when implementing conformal map projections on the ellipsoid.

Creation

Syntax

```
converter = map.geodesy.ConformalLatitudeConverter  
converter = map.geodesy.ConformalLatitudeConverter(spheroid)
```

Description

`converter = map.geodesy.ConformalLatitudeConverter` creates a `ConformalLatitudeConverter` object for a sphere and sets the `Eccentricity` property to 0.

`converter = map.geodesy.ConformalLatitudeConverter(spheroid)` creates a conformal latitude converter object and sets the `Eccentricity` property to match the specified spheroid object.

Input Arguments

spheroid — Reference spheroid

referenceEllipsoid | oblateSpheroid | referenceSphere

Reference spheroid, specified as a referenceEllipsoid, oblateSpheroid, or referenceSphere object. To create a spheroid object, use the creation function specific to the object, or the wgs84Ellipsoid function.

Example: spheroid = referenceEllipsoid('GRS 80');

Properties

Eccentricity — Ellipsoid eccentricity

0 | numeric scalar

Ellipsoid eccentricity, specified as a numeric scalar. Eccentricity is in the interval [0, 0.5]. Eccentricities larger than 0.5 are possible in theory, but do not occur in practice and are not supported.

Data Types: double

Object Functions

forward Convert geodetic latitude to authalic, conformal, isometric, or rectifying latitude
 inverse Convert authalic, conformal, isometric, or rectifying latitude to geodetic latitude

Examples

Create a Conformal Latitude Converter Object and Set Property

```
grs80 = referenceEllipsoid('GRS 80');  
  
conv1 = map.geodesy.ConformalLatitudeConverter;  
conv1.Eccentricity = grs80.Eccentricity
```

```
conv1 =  
  ConformalLatitudeConverter with properties:  
    Eccentricity: 0.0818
```

Create a Conformal Latitude Converter Object Specifying a Spheroid

```
grs80 = referenceEllipsoid('GRS 80');  
conv2 = map.geodesy.ConformalLatitudeConverter(grs80)  
conv2 =  
  ConformalLatitudeConverter with properties:  
    Eccentricity: 0.0818
```

See Also

Functions

[geocentricLatitude](#) | [parametricLatitude](#)

Objects

[AuthalicLatitudeConverter](#) | [IsometricLatitudeConverter](#) | [RectifyingLatitudeConverter](#)

Introduced in R2013a

contains

Package: map.rasterref

Determine if geographic or map raster contains points

Syntax

```
tf = contains(R, lat, lon)
tf = contains(R, xWorld, yWorld)
```

Description

`tf = contains(R, lat, lon)` determines whether the points (lat, lon) in geographic coordinates fall within the bounds of geographic raster R.

`tf = contains(R, xWorld, yWorld)` determines whether the points (xWorld, yWorld) in the world coordinate system fall within the bounds of map raster R contains .

Examples

Check If Single Point Exists Within Bounds of Planar Raster

Create a MapPostingsReference raster reference object.

```
xWorldLimits = [207000 208000];
yWorldLimits = [912500 913000];
rasterSize = [11 21];
R = maprefpostings(xWorldLimits, yWorldLimits, rasterSize, 'ColumnsStartFrom', 'north')
```

```
R =
  MapPostingsReference with properties:
```

```
  XWorldLimits: [207000 208000]
  YWorldLimits: [912500 913000]
  RasterSize: [11 21]
```

```
RasterInterpretation: 'postings'  
  ColumnsStartFrom: 'north'  
  RowsStartFrom: 'west'  
SampleSpacingInWorldX: 50  
SampleSpacingInWorldY: 50  
RasterExtentInWorldX: 1000  
RasterExtentInWorldY: 500  
  XIntrinsicLimits: [1 21]  
  YIntrinsicLimits: [1 11]  
TransformationType: 'rectilinear'  
CoordinateSystemType: 'planar'
```

Check if the raster contains the point (207549,912753). The expected result is 1 (true) since the x-coordinate is within `R.XWorldLimits` and the y-coordinate is within `R.YWorldLimits`.

```
tf = contains(R,207549,912753)
```

```
tf = logical  
    1
```

Check If Multiples Points Exist Within Bounds of Geographic Raster

Create a `GeographicCellsReference` raster reference object.

```
latlim = [0 89];  
lonlim = [-180 179];  
rasterSize = [90 360];  
R = georefcells(latlim,lonlim,rasterSize,'ColumnsStartFrom','north')
```

```
R =  
  GeographicCellsReference with properties:
```

```
  LatitudeLimits: [0 89]  
  LongitudeLimits: [-180 179]  
  RasterSize: [90 360]  
  RasterInterpretation: 'cells'  
  ColumnsStartFrom: 'north'  
  RowsStartFrom: 'west'
```

```

CellExtentInLatitude: 0.988888888888889
CellExtentInLongitude: 0.997222222222222
RasterExtentInLatitude: 89
RasterExtentInLongitude: 359
  XIntrinsicLimits: [0.5 360.5]
  YIntrinsicLimits: [0.5 90.5]
CoordinateSystemType: 'geographic'
  AngleUnit: 'degree'

```

Check if points exist within the northern hemisphere.

```

pts_lat = [32 0 -10 32 212];
pts_lon = [-80 0 80 360 -80];
tf = contains(R,pts_lat,pts_lon)

```

```

tf = 1x5 logical array

```

```

    1    1    0    1    0

```

The first point is in the northern hemisphere. The second point is the origin, and `tf(2)` indicates the origin exists within the bounds of the northern hemisphere. The third point is in the southern hemisphere. The fourth point is identical to the first point after longitude wrapping. The element `tf(4)` demonstrates that the geographic raster supports wrapping of longitude coordinates. The last element `tf(5)` indicates that the geographic raster does not support wrapping of latitude coordinates.

Input Arguments

R — Geographic or map raster

GeographicCellsReference, GeographicPostingsReference, MapCellsReference, or MapPostingsReference object

Geographic or map raster, specified as a GeographicCellsReference, GeographicPostingsReference, MapCellsReference, or MapPostingsReference object.

lat — Latitude coordinates

numeric scalar or vector

Latitude coordinates, specified as a numeric scalar or vector.

Data Types: `single` | `double`

lon — Longitude coordinates

numeric scalar or vector

Longitude coordinates, specified as a numeric scalar or vector. Elements of `lon` can be wrapped arbitrarily without affecting the result.

Data Types: `single` | `double`

xWorld — x-coordinates in the world coordinate system

numeric scalar or vector

x-coordinates in the world coordinate system, specified as a numeric scalar or vector.

Data Types: `single` | `double`

yWorld — y-coordinates in the world coordinate system

numeric scalar or vector

y-coordinates in the world coordinate system, specified as a numeric scalar or vector.

Data Types: `single` | `double`

Output Arguments

tf — Flag indicating geographic or map raster vector contains points in the world coordinate system

logical scalar or vector

Flag indicating geographic or map raster vector contains points in the world coordinate system, returned as a logical scalar or vector. The k th element of `tf` is `True` when `R` contains the point (`xWorld(k)`, `yWorld(k)`) in the world coordinate system.

Data Types: `logical`

See Also

Introduced in R2013b

contour3m

Project 3-D contour plot of map data

Description

The `contour3m` function is the same as the `contourm` function except that the lines for each contour level are drawn in their own horizontal plane, at the z -coordinate equal to the value of that level.


Examples

Contour EGM96 Geoid Heights as 3-D Surface

This example shows how to contour the EGM96 geoid heights in an ordinary axes as a 3-D surface with 50 levels and set the contour line color to black.


Load the geoid.

```
figure('Color','white')
load geoid
contour3m(geoid,geoidrefvec,50,'LineColor','black');
```




Add the geoid as a surface.

```
hold on  
geoshow(geoid,geoidrefvec, 'DisplayType', 'surface')
```



Add a title.


```
title('EGM96 Global Geoid Heights with 50 Contour Levels');
```



View in 3-D.

`view(3)`

EGM96 Global Geoid Heights with 50 Contour Levels



Contour topography and bathymetry of South Asia


This example shows how to contour in a map axes the topography and bathymetry of South Asia and the northern Indian Ocean with a contour interval of 500 meters.

Load topo.

```
load topo
latlim = [ 0 50];
lonlim = [35 115];
[Z, refvec] = maptrims(topo, topolegend, latlim, lonlim);
```




```
figure('Color','white')
axesm('lambertstd','MapLatLimit',latlim,'MapLonLimit',lonlim)
tightmap; axis off
contour3m(Z,refvec,'black','LevelStep',500)
```



Add the geoid as a surface and set the colormap.


```
geoshow(Z,refvec,'DisplayType','surface')
demcmmap(Z)
```



Add a title.

```
title({'South Asia Topography and Bathymetry', ...  
      'with 500 m Contours'});
```



**South Asia Topography and Bathymetry
with 500 m Contours**



View in 3-D

```
set(gca, 'DataAspectRatio', [1 1 40000])  
view(3)
```

South Asia Topography and Bathymetry with 500 m Contours



Tips

- If you use `contour3m` with the `globe` map display, the `contour3m` function warns. Be careful to scale the input data relative to the radius of your reference sphere.

See Also

`clabel` | `clabelm` | `clegendm` | `contour` | `contour3` | `contourfm` | `contourm` | `geoshow` | `plot`

Introduced before R2006a

contourcbar

Color bar for filled contour map display

Syntax

```
H = contourcbar(...)
```

Description


`H = contourcbar(...)` creates a color bar associated with a filled contour display created with `contourfm`, `contourm`, `contour3m`, or `geoshow`. It supports the same syntax and usage options as the MATLAB function `colorbar`.

Examples

Add colorbar to map showing topography of North America

Create world map.

```
figure('Color','white')  
worldmap('north america')
```



Load topographical data from MAT-file `topo.mat` .


```
load topo
```

Create geographic raster reference object.

```
R = georasterref('RasterSize',[180 360], ...
    'Latlim',topolatlim,'Lonlim',topolonlim);
```


Create a contour plot where every contour is filled with a particular color.

```
contourfm(topo, R, -7000:1000:3000)
caxis([-8000 4000])
```



Add a color bar to the figure to explain the color used with the contours.


contourcbar



Add Colorbar to Map, Showing Geoid with Non-Uniform Levels


Create a world map.

```
figure('Color','white')  
ax = worldmap('world');
```



Move the meridian labels to the bottom, and reduce the number of labels.

```
setm(ax, 'MLabelParallel', -90)  
setm(ax, 'MLabelLocation', 90)
```

Load the geoid data set MAT-file.


```
load geoid60c
```

Specify levels (in meters) at which to contour the geoid.

```
levels = [-70 -40 -20 -10 0 10 20 40 70];
```

Display the geoid as a filled contour plot.

```
geoshow(geoid60c, geoid60cR, 'DisplayType', 'contour', ...  
        'LevelList', levels, 'Fill', 'on', 'LineColor', 'black')
```




Load the coastline data MAT file, `coastlines.mat` .

```
load coastlines
```


Overlay the coastlines.

```
geoshow(coastlat, coastlon, 'Color', 'white', 'LineWidth', 1.5)
```




Add a color bar to indicate the range in geoid height spanned by each contour interval.

```
cb = contourbar('peer',ax,'Location','southoutside');
```



Reset the color map and the axes color limits (CLim).

```
caxis([-110 90])  
colormap(hsv)  
cb.XLabel.String = 'Geoid Undulation in Meters';
```



Tips

- If a *peer* axes is specified when calling `contourbar`, it should be a map axes containing an object created using one of the Mapping Toolbox functions listed previously. Otherwise the current axes should contain such an object.
- If a Mapping Toolbox contour object is present, then the color bar is filled with solid blocks of color which bound each other at the contour levels used in the plot. Thus, the contour levels bounding a fill polygon of a given color can be inferred graphically by inspecting the upper and lower limits of the corresponding block in the color bar. In the absence of a Mapping Toolbox contour object an ordinary color bar is created.

- If multiple Mapping Toolbox contour objects are present in the same axes, then the levels used to divide the color bar into blocks will correspond to the first contour object that is found. This situation could occur when a larger data set is broken up into multiple grid tiles, for example, but as long the tiles all use the same contour level list, the color bar will correctly represent them all.

See Also

`clegendm` | `colorbar` | `contourfm`

Introduced in R2011b

contourmap

Contour colormap and colorbar for current axes

Syntax

```
contourmap(cmapstr)
contourmap(cmapstr,cdelta)
contourmap(...,Name,Value)
h = contourmap(...)
```

Description

`contourmap(cmapstr)` updates the figure's colormap for the current axes with the colormap specified by `cmapstr`. If the axes contains Mapping Toolbox contour objects, the resultant colormap contains the same number of colors as the original colormap. Otherwise, the resultant colormap contains ten colors.

`contourmap(cmapstr,cdelta)` updates the figure's colormap with colors varying according to `cdelta`. If the axes contains Mapping Toolbox contour objects, the value of `cdelta` is ignored.

`contourmap(...,Name,Value)` allows you to add a colorbar and control the colorbar's properties. Parameter names can be abbreviated and are case-insensitive.

`h = contourmap(...)` returns a handle to the colorbar axes.

Input Arguments

cmapstr

A character vector that specifies a colormap. Valid entries for `cmapstr` include 'pink', 'hsv', 'jet', or the name of any similar MATLAB colormap function.

cdelta

A scalar or vector. If `cdelta` is a scalar, it represents a step size, and colors are generated at multiples of `cdelta`. If `cdelta` is a vector of evenly spaced values, colors are generated at those values; otherwise an error is issued.

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

Colorbar

Character vector with values 'on' or 'off' specifying whether a colorbar is present, 'on', or absent from the axes, 'off'.

Default: 'off'

Location

Character vector specifying the location of the colorbar. Permissible values are 'vertical', 'horizontal', or 'none'.

Default: 'vertical'

ColorAlignment

Character vector specifying the alignment of the labels in the colorbar. Permissible values are 'center', where the labels are centered on the color bands, or 'ends', where the labels are centered on the color breaks. If the axes contains Mapping Toolbox contour objects, the `ColorAlignment` will be set automatically to 'center' for contour lines and 'ends' for filled contours, and cannot be modified.

SourceObject

Handle of the graphics object which is used to determine the color limits for the colormap. The `SourceObject` value is the handle of a currently displayed object.

Default: `gca`

TitleString

Title of the colorbar axes, specified as a character vector.

XLabelString

X label of the colorbar axes, specified as a character vector.

YLabelString

Y label of the colorbar axes, specified as a character vector.

ZLabelString

Z label of the colorbar axes, specified as a character vector. In addition, properties and values that can be applied to the title and labels of the colorbar axes are valid.

Output Arguments

h


A handle to the colorbar axes.

Examples

Display World Map with Colormap

This example shows how to display a world map with a colormap representing contour intervals in meters.

```
load topo
R = georasterref('RasterSize', size(topo), ...
    'Latlim', [-90 90], 'Lonlim', [0 360]);
figure('Color', 'white')
worldmap(topo, R)
contourfm(topo, R);
contourmap('jet', 'Colorbar', 'on', ...
    'Location', 'horizontal', ...
    'TitleString', 'Contour Intervals in Meters');
```



Display World Map with Colormap with Custom Contour Intervals

This example shows how to display a world map with a colormap in which the colors vary at a step size of 2000.

Load data from MAT-files.


```
load topo
load coastlines
```

Create a raster reference object associated with the topo data set.

```
R = georefcells(topolatlim,topolonlim,size(topo));
```


Display the topo data set on a worldmap.

```
figure('Color','white')  
worldmap(topo,R)  
geoshow(topo,R,'DisplayType','texturemap');
```




Change the color map of the contours.

```
contourmap('summer',2000,'Colorbar','on', ...  
          'Location','horizontal', ...  
          'TitleString','Contour Intervals in Meters');
```



Display coastlines on the map.

```
geoshow(coastlat,coastlon,'Color','black')
```



See Also

[clabelm](#) | [clegendm](#) | [colormap](#) | [contour3m](#) | [contourcbar](#) | [contourfm](#) | [contourm](#)

Introduced before R2006a

contourfm

Project filled 2-D contour plot of map data

Description

The `contourfm` function is the same as the `contourm` function except that the areas between contours are filled with colors. For each contour interval, `contourfm` selects a distinct color from the figure's colormap. You can obtain the same result by setting `'Fill', 'on'` and `'LineColor', 'black'` when calling `contourm`.

Examples

Plot Earth's Geoid with Filled Contours


This example shows how to plot the Earth's geoid with filled contours, measure in meters.

```
figure
axesm eckert4; framem; gridm; axis off; tightmap

load geoid
contourfm(geoid, geoidrefvec, -120:20:100, 'LineStyle', 'none');

load coastlines
geoshow(coastlat, coastlon, 'Color', 'black')

contourcbar
```



See Also

[clabelm](#) | [contour3m](#) | [contourcbar](#) | [contourm](#) | [meshm](#) | [surfm](#)

Introduced before R2006a

contourm

Project 2-D contour plot of map data

Syntax

```
contourm(Z,R)
contourm(lat,lon,Z)
contourm( ____,n)
contourm( ____,V)
contourm( ____,LineStyle)
contourm( ____,Name,Value)
C = contourm( ____)
[C,h] = contourm( ____)
```

Description

`contourm(Z,R)` creates a contour plot of the regular data grid `Z` with geographic reference `R`.

`contourm(lat,lon,Z)` displays a contour plot of the geolocated data grid, `Z` with geolocation defined by `lat` and `lon`.

`contourm(____,n)` draws `n` contour levels.

`contourm(____,V)` draws contours at the levels specified by `V`.

`contourm(____,LineStyle)` uses any valid `LineStyle` to draw the contour lines.

`contourm(____,Name,Value)` allows you to set optional parameters. Parameter names can be abbreviated, and case does not matter. In addition, any of the following `hggroup` properties can be specified: `'HandleVisibility'`, `'Parent'`, `'Tag'`, `'UserData'`, and `'Visible'`.

`C = contourm(____)` returns a standard contour matrix `C`, with the first row representing longitude data and the second row representing latitude data.

`[C,h] = contourm(___)` returns the contour matrix and the handle to the contour patches drawn onto the current axes. The handle is of type `hggroup`.

Examples


Display Contours for EGM96 Geoid Heights

Load EGM96 geoid heights.

```
load geoid
```


Display contours.

```
figure  
[c,h] = contourm(geoid,geoidrefvec,'LevelStep',20,'ShowText','on');
```



Add axes labels and a legend.

```
xlabel('Longitude')  
ylabel('Latitude')  
clegendm(c,h,-1)
```



Display Contour Geoid Heights for Area Including Korea


Contour geoid heights for an area including Korea with a backdrop of terrain elevations and bathymetry.

Load geoid heights and Korea data.

```
load korea5c  
load geoid60c
```


Create a map axes that includes Korea.

```
figure  
worldmap(korea5c, korea5cR)
```




Display the digital elevation data and apply a colormap.

```
geoshow(korea5c, korea5cR, 'DisplayType', 'texturemap')  
demcmap(korea5c)
```




Display contours of the geoid values from -100 to 100 in increments of 5.

```
[c,h] = contourm(geoid60c,geoid60cR,-100:5:100,'k');
```



Add red labels with white backgrounds to the contours.

```
t = clabelm(c,h);  
set(t,'Color','r')  
set(t,'BackgroundColor','white')  
set(t,'FontWeight','bold')
```



Input Arguments

Z — Regular or geolocated data grid

M-by-*N* matrix

Regular or geolocated data grid, specified as an *M*-by-*N* matrix.

If the grid contains regions with missing data, set the corresponding elements of *Z* to NaN. Contour lines terminate when entering such areas. Similarly, if you use 'Fill', 'on' or call `contourfm`, such null-data areas will not be filled. If you use the syntax `contourm(lat, lon, Z, ...)`, however, `lat` and `lon` must have finite, non-NaN

values everywhere. In this case, set `Z` to `NaN` in null data areas, but make sure the corresponding elements of `lat` and `lon` have finite values that specify actual locations on the Earth.

R — Geographic reference

geographic raster reference object | vector | matrix

Geographic reference, specified as one of the following. For more information about referencing vectors and matrices, see “Georeferenced Raster Data”.

| Type | Description |
|------------------------------------|---|
| Geographic raster reference object | <code>GeographicCellsReference</code> or <code>GeographicPostingsReference</code> geographic raster reference object. The <code>RasterSize</code> property must be consistent with the size of the data grid, <code>size(Z)</code> . |
| Vector | 1-by-3 numeric vector with elements: [cells/degree northern_latitude_limit western_longitude_limit] |
| Matrix | 3-by-2 numeric matrix that transforms raster row and column indices to or from geographic coordinates according to: [lon lat] = [row col 1] * R R defines a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. For more information about referencing vectors and matrices, see “Georeferenced Raster Data”. If the current axis is a map axis, the coordinates of <code>Z</code> are projected using the projection structure from the axis. The contours are drawn at their corresponding <code>Z</code> level. |

lat, lon — Geolocation array

M-by-*N* matrix | *M*-element vector

Geolocation array with latitude or longitude coordinates, specified as a matrix of the same size as `Z`, or a vector with length matching the number of rows in `Z`.

n — Number of contour levels

numeric scalar

Number of contour levels, specified as a numeric scalar.

V — Value of contour levels

numeric vector

Value of contour levels, specified as a numeric vector with length greater than or equal to two. Use $V = [v \ v]$ to compute a single contour at level v .

LineStyle — Line specification

LineStyle

Line specification, specified as a LineSpec.

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1,Value1,...,NameN,ValueN`.

Example: `'LabelSpacing',72`

Fill — Color areas between contour lines`'off'` (default) | `'on'`

Color areas between contour lines, specified as the comma-separated pair consisting of `'Fill'` and `'off'` or `'on'`. By default `contourm` draws a line (which may have multiple parts) for each contour level. If you set `Fill` to `'on'`, then `contourm` colors the polygonal regions between the lines, selecting a distinct color for each contour interval from the colormap of the figure in which the contours are drawn. Setting `Fill` to `'on'` is almost the same as calling `contourfm`; the only difference is that `contourfm` also sets `LineColor` to black by default.

LabelSpacing — Spacing between labels

numeric scalar

Spacing between labels on each contour line, specified as the comma-separated pair consisting of `'LabelSpacing'` and a numeric scalar. When you display contour line labels either by calling `clabelm` or by specifying `'ShowText','on'`, the labels by

default are spaced 144 points (2 inches) apart on each line. You can specify the spacing by setting `LabelSpacing` to a value in points. If the length of an individual contour line is less than the specified value, only one contour label is displayed on that line.

LevelList — Values at which contour lines are drawn

numeric vector

Values at which contour lines are drawn, specified as the comma-separated pair consisting of `'LevelList'` and a numeric vector. This property uses a row vector of increasing values to specify the levels at which contour lines are drawn.

LevelStep — Spacing of contour lines

positive real scalar

Spacing of contour lines, specified as the comma-separated pair consisting of `'LevelStep'` and a numeric scalar. The `contourm` function draws contour lines at regular intervals determined by the value of `LevelStep`, unless the optional third argument, `n` (number of contour levels) or `V` (vector specifying contour levels) is provided. If `n` or `V` is used in combination with the `LevelStep` parameter, then the `LevelStep` parameter is ignored. If `n`, `V`, and the `LevelStep` parameter are all omitted, `contourm` selects a uniform step automatically.

LineColor — Contour line colors

`'flat'` (default) | `ColorSpec` | `'none'`

Contour line colors, specified as the comma-separated pair consisting of `'LineColor'` and `'flat'`, a `ColorSpec`, or `'none'`. To specify a single color to be used for all the contour lines, you can specify a `ColorSpec` consisting of a three-element RGB vector or one of the MATLAB predefined names. If you omit `LineColor` or set it to `'flat'`, `contourm` selects a distinct color for lines at each contour level from the colormap of the figure in which the contours are drawn. If you set `LineColor` to `'none'`, the contour lines will not be visible.

LineStyle — Line style for contour lines

`'-'` (default) | `'--'` | `':'` | `'-.'` | `'none'`

Line style for contour lines, specified as the comma-separated pair consisting of `'LineStyle'` and `'-'` (solid), `'--'` (dashed), `':'` (dotted), `'-.'` (dash-dot), or `'none'`. The specifiers work the same as for line objects in MATLAB graphics.

LineWidth — Width of contour lines in points

0.5 (default) | numeric scalar

Width of contour lines in points, specified as the comma-separated pair consisting of 'LineWidth' and a numeric scalar. 1 point = 1/72 inch.

ShowText — Flag to display labels on contour lines

'off' (default) | 'on'

Flag to display labels on contour lines, specified as the comma-separated pair consisting of 'ShowText' and 'off' or 'on'. If you set ShowText to 'on', contourm displays text labels on each contour line indicating the value of the corresponding contour level. Another way to add labels to your contour lines is to call `clabelm` after calling contourm.

Output Arguments

C — Contour matrix

numeric matrix

Standard contour matrix, returned as a matrix with two rows. The first row represents longitude data and the second row represents latitude data.

h — Handle of contour patches

hggroup

Handle to the contour patches drawn onto the current axes, returned as an hggroup.

Tips

- You have three ways to control the number of contour levels that display in your map:
 - 1 Set the number of contour levels by specifying the scalar `n` in the syntax `contourm(Z,R,n)` or `contourm(lat,lon,Z,n)`.
 - 2 Use the vector `V` to specify the levels at which contours are drawn with the syntax `contourm(Z,R,V)` or `contourm(lat,lon,Z,V)`.
 - 3 Choose regular intervals at which the contours are drawn by setting the `LevelStep` parameter.

If you do not use any of the above methods to set your contour levels, the contourm function displays around five contour levels.

See Also

`clabelm` | `clegendm` | `contour` | `contour3` | `contour3m` | `contourc` | `contourfm` | `geoshow` | `plot`

Introduced before R2006a

convertlat

Convert between geodetic and auxiliary latitudes

Syntax

```
latout = convertlat(ellipsoid,latin,from,to,units)
```

Description

`latout = convertlat(ellipsoid,latin,from,to,units)` converts latitude values in `latin` from type `from` to type `to`. `ellipsoid` is a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`.

`latin` is an array of input latitude values. `from` and `to` are each one of the latitude types listed below:

| Latitude Type | Description |
|---------------|---|
| geodetic | The geodetic latitude is the angle that a line perpendicular to the surface of the ellipsoid at the given point makes with the equatorial plane. |
| authalic | The authalic latitude maps an ellipsoid to a sphere while preserving surface area. Authalic latitudes are used in place of the geodetic latitudes when projecting the ellipsoid using an equal area projection. |
| conformal | The conformal latitude maps an ellipsoid conformally onto a sphere. Conformal latitudes are used in place of the geodetic latitudes when projecting the ellipsoid with a conformal projection. |
| geocentric | The geocentric latitude is the angle that a line connecting a point on the surface of the ellipsoid to its center makes with the equatorial plane. |

| Latitude Type | Description |
|---------------|--|
| isometric | The isometric latitude is a nonlinear function of the geodetic latitude. |
| parametric | The parametric latitude of a point on the ellipsoid is the latitude on a sphere of radius a , where a is the semimajor axis of the ellipsoid, for which the parallel has the same radius as the parallel of geodetic latitude. |
| rectifying | The rectifying latitude is used to map an ellipsoid to a sphere in such a way that distance is preserved along meridians. |

`latin` has the angle units specified by `units`: either 'degrees' or 'radians'. The output array, `latout`, has the same size and units as `latin`.

To properly project rectified latitudes, the radius must also be scaled to ensure the equal meridional distance property. This is accomplished by `rsphere`.


Examples

```
% Plot the difference between the auxiliary latitudes
% and geocentric latitude, from equator to pole,
% using the GRS 80 ellipsoid. Avoid the polar region with
% the isometric latitude, and scale down the difference
% by a factor of 200.
grs80 = referenceEllipsoid('grs80');
geodetic = 0:2:90;
authalic = ...
conformal = ...
convertpatlat(grs80,geodetic,'geodetic','conformal', 'deg');
geocentric = ...
convertpatlat(grs80,geodetic,'geodetic','geocentric','deg');
parametric = ...
convertpatlat(grs80,geodetic,'geodetic','parametric','deg');
rectifying = ...
convertpatlat(grs80,geodetic,'geodetic','rectifying','deg');
isometric = ...
convertpatlat(grs80,geodetic(1:end-5), ...
'geodetic','isometric','deg');
plot(geodetic, (authalic - geodetic),...
geodetic, (conformal - geodetic),...
```

```

geodetic, (geocentric - geodetic),...
geodetic, (parametric - geodetic),...
geodetic, (rectifying - geodetic),...
geodetic(1:end-5), (isometric - geodetic(1:end-5))/200);
title('Auxiliary Latitudes vs. Geodetic')
xlabel('geodetic latitude, degrees')
ylabel('departure from geodetic, degrees');
legend('authalic','conformal','geocentric', ...
'parametric','rectifying', 'isometric/200',...
'Location','NorthWest');

```



See Also

[oblateSpheroid](#) | [referenceEllipsoid](#) | [referenceSphere](#) | [rsphere](#)

Introduced before R2006a

crossfix

Cross-fix positions from bearings and ranges

Syntax

```
[newlat,newlon] = crossfix(lat,lon,az)
[newlat,newlon] = crossfix(lat,lon,az_range,case)
[newlat,newlon] = crossfix(lat,lon,az_range,case,drlat,drlon)
[newlat,newlon] = crossfix(lat,lon,az,units)
[newlat,newlon] = crossfix(lat,lon,az_range,case,units)
[newlat,newlon] = crossfix(lat,lon,az_range,drlat,drlon,units)
[newlat,newlon] = crossfix(lat,lon,az_range,case,drlat,drlon,units)
mat = crossfix(...)
```

Description

`[newlat,newlon] = crossfix(lat,lon,az)` returns the intersection points of all pairs of great circles passing through the points given by the column vectors `lat` and `lon` that have azimuths `az` at those points. The outputs are two-column matrices `newlat` and `newlon` in which each row represents the two intersections of a possible pairing of the input great circles. If there are n input objects, there will be n choose 2 pairings.

`[newlat,newlon] = crossfix(lat,lon,az_range,case)` allows the input `az_range` to specify either azimuths or ranges. Where the vector `case` equals 1, the corresponding element of `az_range` is an azimuth; where `case` is 0, `az_range` is a range. The default value of `case` is a vector of ones (azimuths).

`[newlat,newlon] = crossfix(lat,lon,az_range,case,drlat,drlon)` resolves the ambiguities when there is more than one intersection between two objects. The scalar-valued `drlat` and `drlon` provide the location of an estimated (dead reckoned) position. The outputs `newlat` and `newlon` are column vectors in this case, returning only the intersection closest to the estimated point. When this option is employed, if any pair of objects fails to intersect, no output is returned and the warning `No Fix` is displayed.

`[newlat,newlon] = crossfix(lat,lon,az,units)`, `[newlat,newlon] = crossfix(lat,lon,az_range,case,units)`, `[newlat,newlon] =`

`crossfix(lat,lon,az_range,drlat,drlon,units)`, and `[newlat,newlon] = crossfix(lat,lon,az_range,case,drlat,drlon,units)` allow the specification of the angle units to be used for all angles and ranges, where `units` is any valid angle units value. The default value of `units` is `'degrees'`.

`mat = crossfix(...)` returns the output in a two- or four-column matrix `mat`.

This function calculates the points of intersection between a set of objects taken in pairs. Given great circle azimuths and/or ranges from input points, the locations of the possible intersections are returned. This is different from the navigational function `navfix` in that `crossfix` uses great circle measurement, while `navfix` uses rhumb line azimuths and nautical mile distances.


Examples

Find intersections of points on circles

This example shows how to find the intersection of points on circles.

Create map axes.

```
figure('color','w');
ha = axesm('mapproj','mercator', ...
    'maplatlim',[-10 15],'maplonlim',[-10 20],...
    'MLineLocation',5,'PLineLocation',5);
axis off
gridm on
framem on
mlabel on
plabel on
```



Define latitudes and longitudes of three arbitrary points, and then define three radii, all 8 degrees.

```
latpts = [0;5;0];
lonpts = [0;5;10];
radii = [8;8;8];
```

Obtain the intersections of imagined small circles around these points.

```
[newlat,newlon] = crossfix(latpts,lonpts,radii,[0;0;0])
```

```
newlat = 3×2
```

```
7.5594 -2.5744
```


```
6.2529 -6.2529
7.5594 -2.5744
```

```
newlon = 3×2
```

```
-2.6260 7.5770
5.0000 5.0000
12.6260 2.4230
```


Draw red circle markers at the given points.

```
geoshow(latpts,lonpts,'DisplayType','point',...
'markeredgecolor','r','markerfacecolor','r','marker','o')
```



Draw magenta diamond markers at the points of intersection.

```
geoshow(reshape(newlat,6,1),reshape(newlon,6,1),'DisplayType','point',...
        'markeredgecolor','m','markerfacecolor','m','marker','d')
```




Generate a small circle 8 deg radius for each original point.

```
[latc1,lonc1] = scircle1(latpts(1),lonpts(1),radii(1));
[latc2,lonc2] = scircle1(latpts(2),lonpts(2),radii(2));
[latc3,lonc3] = scircle1(latpts(3),lonpts(3),radii(3));
```

Plot the small circles to show the intersections are as determined.

```
geoshow(latc1,lonc1,'DisplayType','line',...
        'color','b','linestyle','-')
```

```
geoshow(latc2,lonc2,'DisplayType','line',...
        'color','b','linestyle','-')
geoshow(latc3,lonc3,'DisplayType','line',...
        'color','b','linestyle','-')
```



Find Intersection when provided with dead reckoning position

Find intersection when a dead reckoning position is provided, (0°,5°E). `crossfix` returns one from each pair (the closest one).

```
[newlat,newlon] = crossfix([0 5 0]',[0 5 10]',...
                          [8 8 8]',[0 0 0]',0,5)
```

```
newlat =
```

```
-2.5744  
6.2529  
-2.5744
```

```
newlon =
```

```
7.5770  
5.0000  
2.4230
```

See Also

[gcxgc](#) | [gcxsc](#) | [navfix](#) | [polyxpoly](#) | [rhxrh](#) | [scxsc](#)

Introduced before R2006a

daspectm

Control vertical exaggeration in map display

Syntax

```
daspectm(zunits)
daspectm(zunits,vfac)
daspectm(zunits,vfac,lat,long)
daspectm(zunits,vfac,lat,long,az)
daspectm(zunits,vfac,lat,long,az,radius)
```

Description

`daspectm(zunits)` sets the 'DataAspectRatio' property of the map axes so that the z-axis is in proportion to the x-and y-projected coordinates. This permits elevation data to be displayed without vertical distortion. The `zunits` parameter specifies the units of the elevation data, and can be any length units recognized by `unitsratio`.

`daspectm(zunits,vfac)` sets the 'DataAspectRatio' property so that the z-axis is vertically exaggerated by the factor `vfac`. If omitted, the default is no vertical exaggeration.

`daspectm(zunits,vfac,lat,long)` sets the aspect ratio based on the local map scale at the specified geographic location. If omitted, the default is the center of the map limits.

`daspectm(zunits,vfac,lat,long,az)` also specifies the direction along which the scale is computed. If omitted, 90 degrees (west) is assumed.

`daspectm(zunits,vfac,lat,long,az,radius)` specifies the radius of the sphere. `radius` can be one of the values supported by `km2deg`, or it can be the (numerical) radius of the desired sphere in `zunits`. If omitted, the default radius of the Earth is used.

Examples

Elevation Map with Vertical Exaggeration


Show the elevation map of the Korean peninsula with a vertical exaggeration factor of 30.

Read data from the MAT-file containing information about the Korean peninsula.

```
load korea
```


Display the data grid.

```
[latlim,lonlim] = limitm(map,refvec);  
worldmap(latlim,lonlim)  
meshm(map,refvec,size(map),map)  
demcmap(map)  
view(3)
```



Set the vertical exaggeration factor.

```
daspectm('m',30)  
tightmap  
camlight
```



Limitations

The relationship between the vertical and horizontal coordinates holds only as long as the geoid or scale factor properties of the map axes remain unchanged. If you change the scaling between geographic coordinates and projected axes coordinates, execute `daspectm` again.

See Also

daspect | paperscale

Introduced before R2006a

dcwdata

Read selected DCW worldwide basemap data

Note `dcwdata` will be removed in a future release. The `VMAPO` dataset has replaced DCW and can be accessed using `vmapo@data`.

Syntax

```
struct = dcwdata(library,latlim,lonlim,theme,topolevel)  
struct = dcwdata(devicename,library,...)  
[struct1, struct2,...] = dcwdata(...,{topolevel1,topolevel2,...})
```

Description

`struct = dcwdata(library,latlim,lonlim,theme,topolevel)` reads data for the specified theme and topology level directly from the DCW CD-ROM. There are four CDs, one for each of the libraries: 'NOAMER' (North America), 'SAS AUS' (Southern Asia and Australia), 'EURASIA' (Europe and Northern Asia), and 'SOAMAFR' (South America and Africa). The desired theme is specified by a two-letter code. A list of valid codes is displayed when an invalid code, such as '?', is entered. The region of interest can be given as a point latitude and longitude or as a region with two-element vectors of latitude and longitude limits. The units of latitude and longitude are degrees. The data covering the requested region is returned, but will include data extending to the edges of the 5-by-5 degree tiles. The result is returned as a Version 1 Mapping Toolbox display structure.

`struct = dcwdata(devicename,library,...)` specifies the logical device name of the CD-ROM for computers that do not automatically name the mounted disk.

`[struct1, struct2,...] = dcwdata(...,{topolevel1,topolevel2,...})` reads several topology levels. The levels must be specified as a cell array with the entries 'patch', 'line', 'point', or 'text'. Entering {'all'} for the topology level argument is equivalent to {'patch', 'line', 'point', 'text'}. Upon output, the data structures are returned in the output arguments by topology level in the same order as they were requested.

Background

The Digital Chart of the World (DCW) is a detailed and comprehensive source of publicly available global vector data. It was digitized from the Operational Navigation Charts (scale 1:1,000,000) and Jet Navigation Charts (1:2,000,000), compiled by the U.S. Defense Mapping Agency (DMA) along with mapping agencies in Australia, Canada, and the United Kingdom. The digitized data was published on four CD-ROMS by the DMA and is distributed by the U.S. Geological Survey (USGS).

The DCW is out of print and has been succeeded by the Vector Map Level 0 (VMAP0).

The DCW organizes data into 17 different themes, such as political/oceans (PO), drainage (DN), roads (RD), or populated places (PP). The data is further tiled into 5-by-5 degree tiles and separated by topology level (patches, lines, points, and text).

Examples

On a Macintosh computer,

```
s = dcwdata('NOAMER',41,-69,'?', 'patch');
```

```
??? Error using ==> dcwdata
Theme not present in library NOAMER
Valid two-letter theme identifiers are:
PO: Political/Oceans
PP: Populated Places
LC: Land Cover
VG: Vegetation
RD: Roads
RR: Railroads
UT: Utilities
AE: Aeronautical
DQ: Data Quality
DN: Drainage
DS: Supplemental Drainage
HY: Hypsography
HS: Supplemental Hypsography
CL: Cultural Landmarks
OF: Ocean Features
PH: Physiography
TS: Transportation Structure
```

```
P0patch = dcwdata('NOAMER',[41 44],[-72 -69],'P0','patch')
P0patch =
1x234 struct array with fields:
    type
    otherproperty
    tag
    altitude
    lat
    long
    tag2
    tag3
```

On an MS-DOS based operating system with the CD-ROM as the 'd:' drive,

```
[RDtext,RDline] = dcwdata('d:','SASAUS',[-48 -34],[164 180],...
    'RD',{'text','line'});
```

On a UNIX® operating system with the CD-ROM mounted as '\cdrom',

```
[P0patch,P0line,P0point,P0text] = dcwdata('\cdrom',...
    'EURNASIA',-48 ,164,'P0',{'all'});
```

Tips

Latitudes and longitudes use WGS84 as a horizontal datum. Elevations are in feet above mean sea level. The data set does not contain bathymetric data.

Some DCW themes do not contain all topology levels. In those cases, empty matrices are returned.

The data is tagged with object descriptions. Some data is provided with alternate tags in `tag2` and `tag3` fields. These alternate tags contain information that supplements the standard tag, such as the names of political entities or values of elevation. The `tag2` field generally has the actual values or codes associated with the data. If the information in the `tag2` field expands to more verbose descriptions, these are provided in the `tag3` field.

Point data for which there are descriptions of both the type and the individual names of objects is returned twice within the structure. The first set is a collection of points of the same type with appropriate tag. The second is a set of individual points with the tag 'Individual Points' and the name of the object in the `tag3` field.

Patches are broken at the tile boundaries. Setting the `EdgeColor` to 'none' and plotting the lines gives the map a normal appearance.

The DCW was published in 1992 based on data compiled some years earlier. The political boundaries do not reflect recent changes such as the dissolution of the Soviet Union, Czechoslovakia, and Yugoslavia. In some cases, the boundaries of the successor nations are present as lower level political units. A new version, called `VMAP0`.

For information about the format of display structures, see "Version 1 Display Structures" on page 1-257 in the reference page for `displaym`.

References

The format and the history of the DCW are described in reference [1] of the Appendix A at the end of this chapter.

See Also

`dcwgaz` | `dcwread` | `dcwrhead` | `displaym` | `extractm` | `mayers` | `updategeostruct` | `vmap0data`

Introduced before R2006a

dcwgaz

Search DCW worldwide basemap gazette file

Note `dcwgaz` will be removed in a future release. The `VMAPO` dataset has replaced DCW and can be explored using `vmap0ui`.

Syntax

```
dcwgaz(library,object)
dcwgaz(devicename,library,object)
mtextstruc = dcwgaz(...)
[mtextstruc,mpointstruc] = dcwgaz(...)
```

Description

`dcwgaz(library,object)` searches the DCW library for items beginning with the character vector `object`. There are four CDs, one for each of the libraries: 'NOAMER' (North America), 'SASAUS' (Southern Asia and Australia), 'EURNASIA' (Europe and Northern Asia), and 'SOAMAFR' (South America and Africa). Items that exactly match or begin with the *object* are displayed on screen.

`dcwgaz(devicename,library,object)` specifies the logical device name of the CD-ROM for computers that do not automatically name the mounted disk.

`mtextstruc = dcwgaz(...)` displays the matched items on screen and returns a Mapping Toolbox display structure with the matches as text entries.

`[mtextstruc,mpointstruc] = dcwgaz(...)` returns the matches in structures formatted both as text and as points.

Background

In addition to the geographic data, the Digital Chart of the World (DCW) also includes an extensive gazette feature. The gazette is a collection of the names of geographic items

mentioned in the various themes of a DCW disk. One DCW disk can contain about 10,000 to 15,000 names. This function allows you to search the gazette for names beginning with a particular character vector.

Examples

On a Macintosh computer,

```
s = dcwgaz('EURNASIA','apatin')
```

```
APATIN
```

```
s =
      type: 'text'
  otherproperty: {1x2 cell}
           tag: 'Built up area'
           string: 'APATIN'
  altitude: []
           lat: 45.6660
           long: 18.9830
```

On a UNIX operating system with the CD-ROM mounted as '\cdrom',

```
[mtextstruc,mpointstruc] = ...
    dcwgaz('\cdrom','SOAMAFR', 'cape good')
```

```
Cape Goodenough
```

```
Cape Goodenough
```

```
Cape Goodenough
```

```
mtextstruc =
```

```
1x3 struct array with fields:
```

```
  type
  otherproperty
  tag
  string
  altitude
  lat
  long
```

```
mpointstruc =
```

```
1x3 struct array with fields:
```

```
  type
  otherproperty
  tag
  string
```

```
altitude  
lat  
long
```

Tips

The search is not case sensitive. Items that match are those that begin with the *object* character vector. Spaces are significant.

See Also

`dcwdata` | `dcwread` | `dcwrhead` | `mlayers` | `updategeestruct`

Introduced before R2006a

dcwread

Read DCW worldwide basemap file

Note `dcwread` will be removed in a future release. The `VMAPO` dataset has replaced DCW and can be read using `vmap0read`.

Syntax

```
dcwread(filepath, filename)
dcwread(filepath, filename, recordIDs)
dcwread(filepath, filename, recordIDs, field, varlen)
struc = dcwread(...)
[struc, field] = dcwread(...)
[struc, field, varlen] = dcwread(...)
[struc, field, varlen, description] = dcwread(...)
[struc, field, varlen, description, narrativefield] = dcwread(...)
```

Description

`dcwread` reads a DCW file. The user selects the file interactively.

`dcwread(filepath, filename)` reads the specified file. The combination [`filepath filename`] must form a valid complete filename.

`dcwread(filepath, filename, recordIDs)` reads selected records or fields from the file. If `recordIDs` is a scalar or a vector of integers, the function returns the selected records. If `recordIDs` is a cell array of integers, all records of the associated fields are returned.

`dcwread(filepath, filename, recordIDs, field, varlen)` uses previously read field and variable-length record information to skip parsing the file header (see below).

`struc = dcwread(...)` returns the file contents in a structure.

`[struc, field] = dcwread(...)` returns the file contents and a structure describing the format of the file.

[struc,field,varlen] = dcwread(...) also returns a vector describing the fields that have variable-length records.

[struc,field,varlen,description] = dcwread(...) also returns, description, a character vector that describes the contents of the file.

[struc,field,varlen,description,narrativefield] = dcwread(...) also returns the name of the narrative file for the current file.

Background

The Digital Chart of the World (DCW) uses binary files in a variety of formats. This function determines the format of the file and returns the contents in a structure. The field names of this structure are the same as the field names in the DCW file.

Examples

The following examples use the Macintosh directory system and file separators for the pathname:

```
s = dcwread('NOAMER:DCW:NOAMER:', 'GRT')
s =
      ID: 1
  DATA_TYPE: 'GEO'
    UNITS: '014'
  ELLIPSOID: 'WGS 84'
ELLIPSOID_DETAIL: 'A=6378137,B=6356752 Meters'
  VERT_DATUM_REF: 'MEAN SEA LEVEL'
  VERT_DATUM_CODE: '015'
    SOUND_DATUM: 'MEAN SEA LEVEL'
  SOUND_DATUM_CODE: '015'
    GEO_DATUM_NAME: 'WGS 84'
    GEO_DATUM_CODE: 'WGE'
  PROJECTION_NAME: 'DECIMAL DEGREES'
```

```
s = dcwread('NOAMER:DCW:NOAMER:AE:', 'INT.VDT')
s =
5x1 struct array with fields:
  ID
  TABLE
```

```
ATTRIBUTE
VALUE
DESCRIPTION
for i = 1:length(s); disp(s(i)); end
    ID: 1
    TABLE: 'AEPOINT.PFT'
    ATTRIBUTE: 'AEPTTYPE'
    VALUE: 1
    DESCRIPTION: 'Active civil'

    ID: 2
    TABLE: 'AEPOINT.PFT'
    ATTRIBUTE: 'AEPTTYPE'
    VALUE: 2
    DESCRIPTION: 'Active civil and military'
    ID: 3
    TABLE: 'AEPOINT.PFT'
    ATTRIBUTE: 'AEPTTYPE'
    VALUE: 3
    DESCRIPTION: 'Active military'

    ID: 4
    TABLE: 'AEPOINT.PFT'
    ATTRIBUTE: 'AEPTTYPE'
    VALUE: 4
    DESCRIPTION: 'Other'

    ID: 5
    TABLE: 'AEPOINT.PFT'
    ATTRIBUTE: 'AEPTTYPE'
    VALUE: 5
    DESCRIPTION: 'Added from ONC when not available from DAFIF'
s = dcwread('NOAMER:DCW:NOAMER:AE:', 'AEPOINT.PFT', 1)
s =
    ID: 1
    AEPTTYPE: 4
    AEPTNAME: 'THULE AIR BASE'
    AEPTVAL: 251
    AEPTDATE: '19900502000000000000'
    AEPTICA0: '1261'
    AEPTDKEY: 'BR17652'
    TILE_ID: 94
    END_ID: 1
```

```
s = dcwread('NOAMER:DCW:NOAMER:AE:', 'AEPOINT.PFT', {1,2})  
s =  
4678x1 struct array with fields:  
    ID  
    AEPTTYPE
```

Tips

This function reads all DCW files except index files (files with names ending in 'X'), thematic index files (files with names ending in 'TI'), and spatial index files (files with names ending in 'SI').

File separators are platform dependent. The *filepath* input must use appropriate file separators, which you can determine using the MATLAB `filesep` function.

See Also

`dcwdata` | `dcwgaz` | `dcwrhead`

Introduced before R2006a

dcwrhead

Read DCW worldwide basemap file headers

Note `dcwrhead` will be removed in a future release. The `VMAPO` dataset has replaced DCW and the header data can be read using `vmap0rhead`.

Syntax

```
dcwrhead
dcwrhead(filepath,filename)
dcwrhead(filepath,filename,fid)
dcwrhead(...)
hdr = dcwrhead(...)
```

Description

`dcwrhead` allows the user to select the header file interactively.

`dcwrhead(filepath,filename)` reads from the specified file. The combination [*filepath filename*] must form a valid complete filename.

`dcwrhead(filepath,filename,fid)` reads from the already open file associated with *fid*.

`dcwrhead(...)` with no output arguments displays the formatted header information on the screen.

`hdr = dcwrhead(...)` returns the DCW header as a character vector.

Background

The Digital Chart of the World (DCW) uses headers in most files to document the contents and format of that file. This function reads the header, displays a formatted version in the command window, or returns it as a character vector.

Examples

The following example uses the Macintosh file separators and pathname:

```
dcwrhead('NOAMER:DCW:NOAMER:AE:', 'AEPOINT.PFT')
Aeronautical Points
AEPOINT.DOC
ID=I,          1,P,Row Identifier,-,-,
AEPTTYPE=I,   1,N,Airport Type,INT.VDT,-,
AEPTNAME=T,   50,N,Airport Name,-,-,
AEPTVAL=I,    1,N,Airport Elevation Value,-,-,
AEPTDATE=D,   1,N,Aeronautical Information Date,-,-,
AEPTICAO=T,   4,N,International Civil Organization Number,-,-,
AEPTDKEY=T,   7,N,DAFIF Reference Number,-,-,
TILE_ID=S,    1,F,Tile Reference Identifier,-,AEPOINT.PTI,
END_ID=I      1,F,Entity Node Primitive Foreign Key,-,-,

s = dcwrhead('NOAMER:DCW:NOAMER:AE:', 'AEPOINT.PFT')
s =
;Aeronautical Points;AEPOINT.DOC;ID=I,          1,P,Row
Identifier,-,-,:AEPTTYPE=I,   1,N,Airport
Type,INT.VDT,-,:AEPTNAME=T,   50,N,Airport Name,-,-,:AEPTVAL=I,
1,N,Airport Elevation Value,-,-,:AEPTDATE=D,   1,N,Aeronautical
Information Date,-,-,:AEPTICAO=T,   4,N,International Civil
Organization Number,-,-,:AEPTDKEY=T,   7,N,DAFIF Reference
Number,-,-,:TILE_ID=S,    1,F,Tile Reference
Identifier,-,AEPOINT.PTI,:END_ID=I      1,F,Entity Node Primitive
Foreign Key,-,-,;;
```

Tips

This function reads all DCW files except index files (files with names ending in 'X'), thematic index files (files with names ending in 'TI'), and spatial index files (files with names ending in 'SI').

File separators are platform dependent. The *filepath* input must use appropriate file separators, which you can determine using the MATLAB `filesep` function.

See Also

`dcwdata` | `dcwgaz` | `dcwread`

Introduced before R2006a

defaultm

Initialize or reset map projection structure

Syntax

```
mstruct = defaultm(projid)  
mstruct = defaultm(mstruct)
```

Description

`mstruct = defaultm(projid)` initializes a map projection structure, where `projid` is a string scalar or character vector that matches one of the entries in the last column of the table displayed by the `maps` function. The output `mstruct` is a map projection structure. It is a scalar structure whose fields correspond to Map Axes Properties.

`mstruct = defaultm(mstruct)` checks an existing map projection structure, sets empty properties, and adjusts dependent properties. The `Origin`, `FFlatLimit`, `FFlatLimit`, `MapLatLimit`, and `MapLonLimit` properties may be adjusted for compatibility with each other and with the `MapProjection` property and (in the case of UTM or UPS) the `Zone` property.

With `defaultm`, you can construct a map projection structure (`mstruct`) that contains all the information needed to project and unproject geographic coordinates using `mfwdtran`, `minvtran`, `vfwdtran`, or `vintran` without creating a map axes or making any use at all of MATLAB graphics. Relevant parameters in the `mstruct` include the projection name, angle units, zone (for UTM or UPS), origin, aspect, false easting, false northing, and (for conic projections) the standard parallel or parallels. In very rare cases you might also need to adjust the frame limit (`FFlatLimit` and `FFlatLimit`) or map limit (`MapLatLimit` and `MapLonLimit`) properties.

You should make exactly two calls to `defaultm` to set up your `mstruct`, using the following sequence:

- 1 Construct a provisional version containing default values for the projection you've selected: `mstruct = defaultm(projection);`

- 2 Assign appropriate values to `mstruct.angleunits`, `mstruct.zone`, `mstruct.origin`, etc.
- 3 Set empty properties and adjust interdependent properties as needed to finalize your map projection structure: `mstruct = defaultm(mstruct)`;

If you've set field `prop1` of `mstruct` to `value1`, field `prop2` to `value2`, and so forth, then the following sequence

```
mstruct = defaultm(projection);  
mstruct.prop1 = value1;  
mstruct.prop2 = value2;  
...  
mstruct = defaultm(mstruct);
```

produces exactly the same result as the following:

```
f = figure;  
ax = axesm(projection, prop1, value1, prop2, value2, ...);  
mstruct = getm(ax);  
close(f)
```

but it avoids the use of graphics and is more efficient.

Note Angle-valued properties are in degrees by default. If you want to work in radians instead, you can make the following assignment in between your two calls to `defaultm`:

```
mstruct.angleunits = 'radians';
```

You must also use values in radians when assigning any angle-valued properties (such as `mstruct.origin`, `mstruct.parallels`, `mstruct.maplatlimit`, `mstruct.maplonlimit`, etc.).

See the Mapping Toolbox User's Guide section on “Work in UTM Without a Displayed Map” for information and an example showing the use of `defaultm` in combination with UTM.

Examples

Create an empty map projection structure for a Mercator projection:

```
mstruct = defaultm('mercator')

mstruct =
  mapprojection: 'mercator'
    zone: []
  angleunits: 'degrees'
    aspect: 'normal'
  falseeasting: []
  falsenorthing: []
  fixedorient: []
    geoid: [1 0]
  maplatlimit: []
  maplonlimit: []
  mapparallels: 0
    nparallels: 1
      origin: []
  scalefactor: []
    trimlat: [-86 86]
    trimlon: [-180 180]
    frame: []
    ffill: 100
  fedgecolor: [0 0 0]
  ffacecolor: 'none'
  flatlimit: []
  flinewidth: 2
  flonlimit: []
    grid: []
  galtitude: Inf
    gcolor: [0 0 0]
  glinestyle: ':'
  glinewidth: 0.5000
  mlineexception: []
    mlinefill: 100
    mlinelimit: []
  mlinelocation: []
  mlinevisible: 'on'
  plineexception: []
    plinefill: 100
    plinelimit: []
  plinelocation: []
  plinevisible: 'on'
    fontangle: 'normal'
    fontcolor: [0 0 0]
    fontname: 'helvetica'
```

```
        fontsize: 9
        fontunits: 'points'
        fontweight: 'normal'
        labelformat: 'compass'
        labelrotation: 'off'
        labelunits: []
        meridianlabel: []
        mlabellocation: []
        mlabelparallel: []
        mlabelround: 0
        parallellabel: []
        plabellocation: []
        plabelmeridian: []
        plabelround: 0
```

Now change the map origin to [0 90 0], and fill in default projection parameters accordingly:

```
mstruct.origin = [0 90 0];
mstruct = defaultm(mstruct)

mstruct =
    mapprojection: 'mercator'
        zone: []
        angleunits: 'degrees'
        aspect: 'normal'
    falseeasting: 0
    falsenorthing: 0
    fixedorient: []
        geoid: [1 0]
    maplatlimit: [-86 86]
    maplonlimit: [-90 270]
    mapparallels: 0
        nparallels: 1
            origin: [0 90 0]
    scalefactor: 1
        trimlat: [-86 86]
        trimlon: [-180 180]
        frame: 'off'
        ffill: 100
    fedgecolor: [0 0 0]
    ffacecolor: 'none'
    flatlimit: [-86 86]
    flinewidth: 2
    flonlimit: [-180 180]
```

```
        grid: 'off'
        galtitude: Inf
        gcolor: [0 0 0]
        glinestyle: ':'
        glinewidth: 0.5
mlineexception: []
        mlinefill: 100
        mlinelimit: []
        mlinelocation: 30
        mlinevisible: 'on'
plineexception: []
        plinefill: 100
        plinelimit: []
        plinelocation: 15
        plinevisible: 'on'
        fontangle: 'normal'
        fontcolor: [0 0 0]
        fontname: 'Helvetica'
        fontsize: 10
        fontunits: 'points'
        fontweight: 'normal'
        labelformat: 'compass'
        labelrotation: 'off'
        labelunits: 'degrees'
meridianlabel: 'off'
mlabellocation: 30
mlabelparallel: 86
        mlabelround: 0
        parallellabel: 'off'
plabellocation: 15
plabelmeridian: -90
        plabelround: 0
```

See Also

`axesm` | `gcm` | `mfwdtran` | `minvtran` | `setm`

Introduced before R2006a

deg2km

Convert spherical distance from degrees to kilometers

Syntax

```
km = deg2km(deg)
km = deg2km(deg, radius)
km = deg2km(deg, sphere)
```

Description

`km = deg2km(deg)` converts distances from degrees to kilometers, as measured along a great circle on a sphere with a radius of 6371 km, the mean radius of the Earth.

`km = deg2km(deg, radius)` converts distances from degrees to kilometers, as measured along a great circle on a sphere having the specified radius.

`km = deg2km(deg, sphere)` converts distances from degrees to kilometers, as measured along a great circle on a sphere approximating an object in the Solar System.

Input Arguments

deg — Distance in degrees

numeric array

Distance in degrees, specified as a numeric array.

Data Types: `single` | `double`

radius — Radius

6371 (default) | numeric scalar

Radius of sphere in units of kilometers, specified as a numeric scalar.

sphere — Sphere

'sun' | 'moon' | 'mercury' | 'venus' | 'earth' | ...

Sphere approximating an object in the Solar System, specified as one of the following values: 'sun', 'moon', 'mercury', 'venus', 'earth', 'mars', 'jupiter', 'saturn', 'uranus', 'neptune', or 'pluto'. The value of sphere is case-insensitive.

Output Arguments

km — Distance in kilometers

numeric array

Distance in kilometers, returned as a numeric array.

Data Types: `single` | `double`

See Also

`deg2nm` | `deg2rad` | `deg2sm` | `km2deg` | `rad2deg` | `rad2km`

Introduced in R2007a

deg2nm

Convert spherical distance from degrees to nautical miles

Syntax

```
nm = deg2nm(deg)
nm = deg2nm(deg, radius)
nm = deg2nm(deg, sphere)
```

Description

`nm = deg2nm(deg)` converts distances from degrees to nautical miles, as measured along a great circle on a sphere with a radius of 3440.065 nm, the mean radius of the Earth.

`nm = deg2nm(deg, radius)` converts distances from degrees to nautical miles, as measured along a great circle on a sphere having the specified radius.

`nm = deg2nm(deg, sphere)` converts distances from degrees to nautical miles, as measured along a great circle on a sphere approximating an object in the Solar System.

Examples

Convert Arc Length to Nautical Miles

One degree of arc length is about 60 nautical miles, using a spherical model of the Earth.

```
deg2nm(1)
```

```
ans =
    60.0405
```

This is not true on Mercury, of course.

```
deg2nm(1, 'mercury')
```

```
ans =  
    22.9852
```

Input Arguments

deg — Distance in degrees

numeric array

Distance in degrees, specified as a numeric array.

Data Types: `single` | `double`

radius — Radius

3440.065 (default) | numeric scalar

Radius of sphere in units of nautical miles, specified as a numeric scalar.

sphere — Sphere

'sun' | 'moon' | 'mercury' | 'venus' | 'earth' | ...

Sphere approximating an object in the Solar System, specified as one of the following values: 'sun', 'moon', 'mercury', 'venus', 'earth', 'mars', 'jupiter', 'saturn', 'uranus', 'neptune', or 'pluto'. The value of `sphere` is case-insensitive.

Output Arguments

nm — Distance in nautical miles

numeric array

Distance in nautical miles, returned as a numeric array.

Data Types: `single` | `double`

See Also

`deg2km` | `deg2rad` | `deg2sm` | `nm2deg` | `rad2deg` | `rad2nm`

Introduced in R2007a

deg2sm

Convert spherical distance from degrees to statute miles

Syntax

```
sm = deg2sm(deg)
sm = deg2sm(deg, radius)
sm = deg2sm(deg, sphere)
```

Description

`sm = deg2sm(deg)` converts distances from degrees to statute miles as measured along a great circle on a sphere with a radius of 3958.748 sm, the mean radius of the Earth.

`sm = deg2sm(deg, radius)` converts distances from degrees to statute miles as measured along a great circle on a sphere having the specified radius.

`sm = deg2sm(deg, sphere)` converts distances from degrees to statute miles, as measured along a great circle on a sphere approximating an object in the Solar System.

Input Arguments

deg — Distance in degrees

numeric array

Distance in degrees, specified as a numeric array.

Data Types: `single` | `double`

radius — Radius

3958.748 (default) | numeric scalar

Radius of sphere in units of statute miles, specified as a numeric scalar.

sphere — Sphere

'sun' | 'moon' | 'mercury' | 'venus' | 'earth' | ...

Sphere approximating an object in the Solar System, specified as one of the following values: 'sun', 'moon', 'mercury', 'venus', 'earth', 'mars', 'jupiter', 'saturn', 'uranus', 'neptune', or 'pluto'. The value of sphere is case-insensitive.

Output Arguments

sm — Distance in statute miles

numeric array

Distance in statute miles, returned as a numeric array.

Data Types: `single` | `double`

See Also

`deg2km` | `deg2nm` | `deg2rad` | `rad2deg` | `rad2sm` | `sm2deg`

Introduced in R2007a

degrees2dm

Convert degrees to degrees-minutes

Syntax

DM = degrees2dm(angleInDegrees)

Description

DM = degrees2dm(angleInDegrees) converts angles from values in degrees which may include a fractional part (sometimes called “decimal degrees”) to degrees-minutes representation.

Examples

Convert Angle in Degrees to Degree-Minutes

```
angleInDegrees = [ 30.8457722555556; ...  
                  -82.0444189583333; ...  
                  -0.504756513888889; ...  
                  0.004116666666667];
```

```
dm = degrees2dm(angleInDegrees)
```

```
dm = 4x2
```

```
    30.0000    50.7463  
   -82.0000     2.6651  
         0   -30.2854  
         0     0.2470
```

Input Arguments

angleInDegrees — Angle in degrees

n-element real-valued column vector

Angle in degrees, specified as an *n*-element real-valued column vector.

Output Arguments

DM — Angle in degrees-minutes representation

n-by-2 real-valued matrix

Angle in degrees-minutes representation, returned as an *n*-by-2 real-valued matrix. Each row specifies one angle, with the format [D M]:

- D contains the “degrees” element and is integer-valued.
- M contains the “minutes” element and may have a fractional part.

In any given row of DM, the sign of the first nonzero element indicates the sign of the overall angle. A positive number indicates north latitude or east longitude; a negative number indicates south latitude or west longitude. Any remaining element in that row has nonnegative values.

See Also

deg2rad | degrees2dms | dm2degrees | rad2deg

Topics

“Angle Representations and Angular Units”

“Angles as Binary and Formatted Numbers”

Introduced in R2007a

degrees2dms

Convert degrees to degrees-minutes-seconds

Syntax

DMS = degrees2dms(angleInDegrees)

Description

DMS = degrees2dms(angleInDegrees) converts angles from values in degrees which may include a fractional part (sometimes called “decimal degrees”) to degrees-minutes-seconds representation.

Examples

Convert Angle in Degrees to Degree-Minute-Seconds

```
angleInDegrees = [ 30.8457722555556; ...
                  -82.0444189583333; ...
                  -0.504756513888889; ...
                  0.004116666666667];
dms = degrees2dms(angleInDegrees)
```

dms = 4×3

| | | |
|----------|----------|---------|
| 30.0000 | 50.0000 | 44.7801 |
| -82.0000 | 2.0000 | 39.9082 |
| 0 | -30.0000 | 17.1235 |
| 0 | 0 | 14.8200 |

Customize Degree-Minute-Seconds Display Format

Convert angles in degrees to degree-minute-second representation. Display the result using the default display provided by `angl2str`.

```
angleInDegrees = [ 30.8457722555556; ...
                  -82.0444189583333; ...
                  -0.504756513888889; ...
                  0.004116666666667];
angl2str(angleInDegrees, 'ns', 'degrees2dms')

ans = 4x25 char array
' 30^\circ 50' 44.78" N '
' 82^\circ 02' 39.91" S '
' 0^\circ 30' 17.12" S '
' 0^\circ 00' 14.82" N '
```

Alternatively, specify a custom display format by converting the angles to degree-minute-second representation and using `sprintf`. The result is a single string.

```
dms = degrees2dms(angleInDegrees)

dms = 4x3

    30.0000    50.0000    44.7801
   -82.0000     2.0000    39.9082
         0   -30.0000    17.1235
         0         0    14.8200

nonnegative = all((dms >= 0),2);
hemisphere = repmat('N', size(nonnegative));
hemisphere(~nonnegative) = 'S';
absvalues = num2cell(abs(dms));
values = [absvalues; num2cell(hemisphere)];
sprintf('%2.0fd:%2.0fm:%7.5fs:%s\n',values{:})

ans =
'30d:50m:44.78012s:N
 82d: 2m:39.90825s:S
 0d:30m:17.12345s:S
 0d: 0m:14.82000s:N
'
```


Input Arguments

angleInDegrees — Angle in degrees

n-element real-valued column vector

Angle in degrees, specified as an *n*-element real-valued column vector.

Output Arguments

DMS — Angle in degrees-minutes-seconds representation

n-by-3 real-valued matrix

Angle in degrees-minutes-seconds representation, returned as an *n*-by-3 real-valued matrix. Each row specifies one angle, with the format [D M S]:

- D contains the “degrees” element and is integer-valued.
- M contains the “minutes” element and is integer-valued.
- S contains the “seconds” element and may have a fractional part.

In any given row of DMS, the sign of the first nonzero element indicates the sign of the overall angle. A positive number indicates north latitude or east longitude; a negative number indicates south latitude or west longitude. Any remaining elements in that row will have nonnegative values.

See Also

deg2rad | degrees2dm | dms2degrees | rad2deg

Topics

“Angle Representations and Angular Units”

“Angles as Binary and Formatted Numbers”

Introduced in R2007a

degtorad

Convert angles from degrees to radians

Note degtorad is not recommended. Use deg2rad instead.

Syntax

```
angleInRadians = degtorad(angleInDegrees)
```

Description

`angleInRadians = degtorad(angleInDegrees)` converts angle units from degrees to radians. This is both an angle conversion function and a distance conversion function, since arc length can be a measure of distance in either radians or degrees, provided that the radius is known.

Examples

Show that there are 2π radians in a full circle:

```
2*pi - degtorad(360)
```

```
ans =  
    0
```

See Also

[fromDegrees](#) | [fromRadians](#) | [rattodeg](#) | [toDegrees](#) | [toRadians](#)

Introduced in R2009b

demcmap

Colormaps appropriate to terrain elevation data

Syntax

```
demcmap(Z)
demcmap(Z,ncolors)
demcmap(Z,ncolors,cmapsea,cmapland)

demcmap('inc',Z,deltaz)
demcmap('inc',Z,deltaz,cmapsea,cmapland)

[cmap,climits] = demcmap( ___ )
```

Description

`demcmap(Z)` sets the colormap and color axis limits based on the elevation data limits derived from input argument `Z`.

- The default colormap assigns shades of green and brown for positive elevations, and various shades of blue for negative elevation values below sea level.
- The number of colors assigned to land and to sea are in proportion to the ranges in terrain elevation and bathymetric depth and total 64 by default. The color axis limits are computed such that the interface between land and sea maps to the zero elevation contour.
- The colormap is applied to the current figure and the color axis limits are applied to the current axes.

`demcmap(Z,ncolors)` creates a colormap of length `ncolors`.

`demcmap(Z,ncolors,cmapsea,cmapland)` assigns `cmapsea` and `cmapland` to elevations below and above sea level respectively.

`demcmap('inc',Z,deltaz)` chooses number of colors and color axis limits such that each color approximately represents the increment of elevation `deltaz`.

- The literal 'inc' signals demcmap that the first argument after Z will be deltaz.

demcmap('inc',Z,deltaz,cmapsea,cmapland) assigns cmapsea and cmapland to elevations below and above sea level respectively.

[cmap,climits] = demcmap(___) returns colormap cmap and color axis limit climits, using any of the above syntaxes, but does not apply them to figure or axes properties.


- Even if only one output argument is specified, no change occurs to figure or axes properties.

Examples

Displaying Elevation Data With Default Colormap

Explicitly determine maximum and minimum values of elevation data matrix


```
load topo
axesm hatano
meshm(topo,topolegend)
zlimits = [min(topo(:)) max(topo(:))];
demcmap(zlimits);
colorbar;
```



Defining Custom Land And Sea Colormaps

Custom RGB colormaps, `cmapsea`; `cmapland`, of differing lengths are used to populate figure colormap by interpolation. The colors in each colormap map to the land and sea regions of the map. Fewer colors have been specified in total than the default number of 64. `demcmap` determines maximum and minimum elevation data limits internally as shown in the below example when the first argument is the elevation data grid.

```
load topo % grid of elevation data
axesm hatano
meshm(topo,topolegend)
cmapsea = [.8 0 .8; 0 0 .8];
cmapland = [.7 0 0; .8 .8 0; 1 1 .8 ];
demcmap(topo,32,cmapsea,cmapland)
colorbar;
```




Colormap in Which Each Color Approximates a User Defined Increment

The following `demcmap` example controls the color quantization by choosing an optimal number of colors such that each color represents an elevation increment of approximately 2000 .

```
load topo
R = georasterref('RasterSize', size(topo),'Latlim', [-90 90], 'Lonlim', [0 360]);
figure('Color','white')
worldmap('world')
geoshow(topo, R, 'DisplayType', 'texturemap')
```

```
demcmap('inc',[max(topo(:)) min(topo(:))],2000);  
colorbar
```



Input Arguments

Z — Terrain elevation limits

vector | matrix

Terrain elevation limits specified as a vector or matrix. If **Z** is a 2 element vector, then it specifies the minimum and maximum limits of terrain elevation data; ordering is not important. If **Z** is a matrix, then it specifies an elevation grid in which positive and negative values represent points above and below sea level respectively. The above two syntaxes for `demcmap` are identical in their effect on the figure colormap and axes properties.

Data Types: `single` | `double` | `int8` | `int32` | `uint8` | `uint16` | `uint32`

ncolors — Number of colors in colormap

64 (default) | scalar

Number of colors in the colormap specified as a scalar. It defines the number of rows *m* in the *mx3* RGB matrix of the figure colormap.

Data Types: `double`

cmapsea, cmapland — RGB colormap matrices

matrix

- RGB colormaps specified as mx3 arrays containing any number of rows. The two colormaps need not be equal in length. They serve as the basis set for populating the figure colormap by interpolation.
- `cmapsea` and `cmapland` replace the default colormap. The default colormap for land or sea can be retained by providing an empty matrix in place of either colormap matrix.

That part of the figure colormap assigned to negative elevations is derived from `cmapsea`; `cmapland` plays a similar role for positive elevations.

Data Types: double

deltaz — Increment of elevation

scalar

The increment of elevation specified as a scalar. The color quantization of the default or user supplied colormap is adjusted such that each discrete color approximately represents a `deltaz` increment in elevation.

Data Types: double

Output Arguments

cmap — RGB colormap

matrix

RGB colormap returned as a matrix constructed for the figure colormap. Supply output arguments when you want to obtain the colormap and color axis limits without applying them automatically to the figure or axes properties. These properties remain unchanged even if only one output (`cmap`) is specified.

Data Types: double

climits — Color axis limits

vector


Color axis limits returned as a vector. `climits` may differ somewhat from those derived from input argument `Z` due to the quantization which results from fitting a limited number of colors over the range limit of the elevation data.

Supply output arguments when you want to obtain the colormap and color axis limits without applying them automatically to the figure or axes.

Data Types: `double`

Algorithms

If the elevation grid data contains both positive and negative values, then the computed colormap, `cmap`, has a “sea” partition of length `nsea` and “land” partition of length `nland`. The sum of `nsea` and `nland` equals the total number of entries in the computed colormap. The actual values of `nsea` and `nland` depend upon the number of entries and the relative range of the negative and positive limits of the elevation data. The sea partition consists of rows 1 through `nsea`, and the land partition consists of rows `nsea + 1` through `ncolors`. The sea and land partitions of the figure colormap are populated with colors interpolated from the basis RGB colormaps, `cmapsea` and `cmapland`. In the figure below, the sea and land 3x3 RGB colormaps shown are the default colors used by `demcmap` to populate the figure colormap when no user specified colormaps are provided.



If the elevation grid data contains only positive or negative values, then the figure colormap is derived solely from the corresponding sea or land colormap.

See Also

caxis | colormap | meshlsrm | meshm | surflsrm | surfm

Introduced before R2006a

departure

Departure of longitudes at specified latitudes

Syntax

```
dist = departure(long1,long2,lat)
dist = departure(long1,long2,lat,ellipsoid)
dist = departure(long1,long2,lat,units)
dist = departure(long1,long2,lat,geoid,units)
```

Description

`dist = departure(long1,long2,lat)` computes the departure distance from `long1` to `long2` at the input latitude `lat`. Departure is the distance along a specific parallel between two meridians. The output `dist` is returned in degrees of arc length on a sphere.

`dist = departure(long1,long2,lat,ellipsoid)` computes the departure assuming that the input points lie on the ellipsoid defined by the input `ellipsoid`. `ellipsoid` is a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`.

`dist = departure(long1,long2,lat,units)` where `units` defines the angle units of the input and output data. In this form, the departure is returned as an arc length in the units specified by `units`. If `units` is omitted, 'degrees' is assumed.

`dist = departure(long1,long2,lat,geoid,units)` is a valid calling form. In this case, the departure is computed in the same units as the semimajor axes of the ellipsoid.

Examples

Calculate Departure Distance on Sphere and Ellipsoid

On a spherical Earth, the departure distance is proportional to the cosine of the latitude. For example, calculate the departure distance for 0°.

```
distance = departure(0, 10, 0)
```

```
distance = 10
```

Now calculate the distance for 60°.

```
distance = departure(0, 10, 60)
```

```
distance = 5.0000
```

When you calculate the same departure distances on an ellipsoid, the result is more complicated. Again, calculate the departure distance for 0°.

```
distance = departure(0, 10, 0, referenceEllipsoid('earth', 'nm'))
```

```
distance = 601.0772
```

Now calculate the distance at 60°. You can see that the value is not exactly half the 0° value.

```
distance = departure(0, 10, 60, referenceEllipsoid('earth', 'nm'))
```

```
distance = 301.2959
```

Definitions

Departure

Departure is the distance along a parallel between two points. Whereas a degree of latitude is always the same distance, a degree of longitude is different in length at different latitudes. In practice, this distance is usually given in nautical miles.

See Also

[distance](#) | [stdm](#)

Introduced before R2006a

disp

Display geographic or planar vector

Syntax

```
disp(v)
```

Description

`disp(v)` prints the size of the geographic or planar vector `v`, and its properties and dynamic properties, if they exist.

If the command window is large enough, the values of the properties are also shown, otherwise only their size is shown. You can control the display of the numerical values using the `format` command.

Examples

Display a Geoshape Vector

Create a geoshape vector.

```
gs = geoshape(shaperead('worldcities', 'UseGeo', true));
```

Display the entire geoshape vector.

```
disp(gs)
```

```
318x1 geoshape vector with properties:
```

```
Collection properties:
```

```
    Geometry: 'point'
```

```
    Metadata: [1x1 struct]
```

```
Vertex properties:
```

```
(318 features concatenated with 317 delimiters)
```

```

    Latitude: [1x635 double]
    Longitude: [1x635 double]
    Feature properties:
        Name: {1x318 cell}

```

Display only the first two feature of the geoshape vector. Notice that the property values are shown because they are short enough to fit on the command window.

```
disp(gs(1:2));
```

```

2x1 geoshape vector with properties:

Collection properties:
    Geometry: 'point'
    Metadata: [1x1 struct]
Vertex properties:
    (2 features concatenated with 1 delimiter)
    Latitude: [5.2985 NaN 24.6525]
    Longitude: [-3.9509 NaN 54.7589]
Feature properties:
    Name: {'Abidjan' 'Abu Dhabi'}

```

Input Arguments

v — Geographic or planar vector to be displayed

geopoint, geoshape, mappoint, or mapshape objects

Geographic or planar vector to be displayed, specified as a geopoint, geoshape, mappoint, or mapshape object.

See Also

fieldnames | format | properties

Introduced in R2012a

disp

Display properties of WMS layers or capabilities

Syntax

```
disp(layers,Name,Value,...)
disp(capabilities)
```

Description

`disp(layers,Name,Value,...)` displays the index number followed by the property names and property values of the Web map service layers, `layers`. You can specify additional options using one or more `Name,Value` pair arguments.

`disp(capabilities)` displays the properties of the Web map service capabilities document, `capabilities`. The function removes hyperlinks and expands character vector and cell array properties.

Examples

Display Specific Properties of WMSLayer Object

Display `LayerTitle` and `LayerName` properties to the command window without an `Index`.

```
layers = wmsfind('srtm30');
disp(layers(1:5),'Index', 'off', ...
      'Properties',{ 'layertitle','layername' });
```

```
5x1 WMSLayer
```

```
Properties:
```

```
LayerTitle: 'SRTM30_PLUS Estimated Topography, 30 seconds, Global, v11 - z'
LayerName: 'srtm30plus:z'
```

```
LayerTitle: 'SRTM30_PLUS Estimated Topography, 30 seconds, Global, v11, Lon+/-180'
LayerName: 'srtm30plus_LonPM180:z'
```

```
LayerTitle: 'Topography, SRTM30+ Version 1.0, 30 arc second, Global - topo'
LayerName: 'usgsCeSrtm30v1:topo'
```

```
LayerTitle: 'Topography, SRTM30+ Version 6.0, 30 arc second, Global - topo'
LayerName: 'usgsCeSrtm30v6:topo'
```

```
LayerTitle: 'SRTM30 with Bathymetry (900m) merged with global ASTER (30m)'
LayerName: 'EarthAsterElevations30m'
```

Sort and Display Property of WMSLayer Object

Sort and display the LayerName property with an index.

Retrieve the layers.

```
layers = wmsfind('elevation');
```

Sort the layers.

```
[layerNames, index] = sort({layers.LayerName});
```

Display as a sample the first five results.

```
layers = layers(index);
disp(layers(1:5), 'Label', 'off', 'Properties', 'layername');
```

```
5x1 WMSLayer
Properties:
    Index: 1
'0'
    Index: 2
'133'
    Index: 3
'134'
```

Index: 4
'141'

Index: 5
'201'

Display WMS Capabilities

Create a `WMSCapabilities` object from the contents of a downloaded capabilities file from the NASA SVS Image Server.

```
nasa = wmsfind('NASA SVS Image', 'SearchField', 'servertitle');  
serverURL = nasa(1).ServerURL;  
server = WebMapServer(serverURL);  
capabilities = server.getCapabilities;
```

Display the properties of the capabilities document.

```
disp(capabilities)
```

Input Arguments

layers — Layers to display

array of `WMSLayer` objects

Layers to display, specified as an array of `WMSLayer` objects.

capabilities — WMS capabilities document to display

`WMSCapabilities` object

WMS capabilities document to display, specified as a `WMSCapabilities` object.

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

You can abbreviate parameter names, and case does not matter.

Example: `'Properties', {'layertitle', 'layername'}`

Properties — Properties to display

`'all'` (default) | character vector or cell array of character vectors

Properties to display, specified as a character vector or cell array of character vectors. The properties are displayed in the same order as they are provided to `Properties`. Permissible values are: `'servertitle'`, `'servername'`, `'layertitle'`, `'layername'`, `'latlim'`, `'lonlim'`, `'abstract'`, `'coordrefsycodes'`, `'details'`, or `'all'`. To list all the properties, set `'Properties'` to `'all'`.

Example: `{'coordrefsycodes', 'latlim', 'lonlim'}`

Label — Flag to display property values

`'on'` (default) | `'off'`

Flag to display property values, specified as the character vector `'on'` or `'off'`. The value is case-insensitive. If you set `'Label'` to `'on'`, then the property name appears followed by its value. If you set `'Label'` to `'off'`, then only the property value appears in the output.

Example: `'off'`

Index — Flag to display property indices

`'on'` (default) | `'off'`

Flag to display property indices, specified as the character vector `'on'` or `'off'`. The value is case-insensitive. If you set `'Index'` to `'on'`, then `disp` lists the element's index in the output. If you set `'Index'` to `'off'`, then `disp` does not list the index value in the output.

Example: `'off'`

See Also

`getCapabilities` | `wmsfind`

Introduced in R2009b

displaym

Display geographic data from display structure

Syntax

```
displaym(displaystruct)
displaym(displaystruct,str)
displaym(displaystruct,strings)
displaym(displaystruct,strings,searchmethod)
h = displaym(displaystruct)
```

Description

`displaym(displaystruct)` projects the data contained in the input `displaystruct`, a Version 1 Mapping Toolbox display structure, in the current axes. The current axes must be a map axes with a valid map definition. See the remarks about “Version 1 Display Structures” on page 1-257 below for details on the contents of display structures.

`displaym(displaystruct,str)` displays the vector data elements of `displaystruct` whose 'tag' field contains character vectors beginning with 'str'. Vector data elements are those whose 'type' field is either 'line' or 'patch'. The match is case-insensitive.

`displaym(displaystruct,strings)` displays the vector data elements of `displaystruct` whose 'tag' field matches with one of the elements (or rows) of `strings`. `strings` is a cell array of character vectors (or a 2-D character array). In the case of character array, trailing blanks are stripped from each row before matching.

`displaym(displaystruct,strings,searchmethod)` controls the method used to match the values of the tag field in `displaystruct`, as follows:

- 'strmatch' — Search for matches at the beginning of the tag
- 'findstr' — Search within the tag
- 'exact' — Search for exact matches

Note that when `searchmethod` is specified the search is case-sensitive.

`h = displaym(displaystruct)` returns handles to the graphic objects created by `displaym`.

Note The type of *display structure* accepted by `displaym` is not the same as a *geographic data structure* (geostructs and mapstructs), introduced in Mapping Toolbox Version 2. Use `geoshow` or `mapshow` instead of `displaym` to display geostructs or mapstructs—created using `shaperead` and `gshhs`, for example. For more information, see “Geographic Data Structures”.

Tips

The following section documents the contents of display structures.

Version 1 Display Structures

A display structure is a MATLAB structure array with the following fields:

- A `tag` field names an individual feature or object
- A `type` field specifies a MATLAB graphics object type ('line', 'patch', 'surface', 'text', or 'light') or has the value 'regular', specifying a regular data grid
- `lat` and `long` fields contain coordinate vectors of latitudes and longitudes, respectively
- An `altitude` field contains a vector of vertical coordinate values
- A `string` property contains text to be displayed if `type` is 'text'
- MATLAB graphics properties are specified explicitly, on a per-feature basis, in an `otherproperty` field

The choice of options for the `type` field reveals that a display structure can contain

- Vector geodata (type is 'line' or 'patch')
- Raster geodata (type is 'surface' or 'regular')
- Graphic objects (type is 'text' or 'light')

The following table indicates which fields are used in the six types of display structures:

| Field Name | Type 'light' | Type 'line' | Type 'patch' | Type 'regular' | Type 'surface' | Type 'text' |
|---------------|--------------|-------------|--------------|----------------|----------------|-------------|
| type | • | • | • | • | • | • |
| tag | • | • | • | • | • | • |
| lat | • | • | • | | • | • |
| long | • | • | • | | • | • |
| map | | | | • | • | |
| maplegend | | | | • | | |
| meshgrat | | | | • | | |
| string | | | | | | • |
| altitude | • | • | • | • | • | • |
| otherproperty | • | • | • | • | • | • |

Some fields can contain empty entries, but each indicated field must exist for the objects in the struct array to be displayed correctly. For instance, the `altitude` field can be an empty matrix and the `otherproperty` field can be an empty cell array.

The `type` field must be one of the specified map object types: 'line', 'patch', 'regular', 'surface', 'text', or 'light'.

The `tag` field must be different from the `type` field usually containing the name or kind of map object. Its contents must not be equal to the name of the object type (i.e., line, surface, text, etc.).

The `lat`, `long`, and `altitude` fields can be scalar values, vectors, or matrices, as appropriate for the map object type.

The `map` field is a data grid. If `map` is a regular data grid, `maplegend` is its corresponding referencing vector, and `meshgrat` is a two-element vector specifying the graticule mesh size. If `map` is a geolocated data grid, `lat` and `long` are the matrices of latitude and longitude coordinates.

The `otherproperty` field is a cell array containing any additional display properties appropriate for the map object. Cell array entries can be a line specification, such as 'r+', or property name/property value pairs, such as 'color', 'red'. If the `otherproperty` field is left as an empty cell array, default colors are used in the display of lines and patches based on the `tag` field.

Note In some cases you can use the `geoshow` function as a direct alternative to `displaym`. It accepts display structures of type `line` and `patch`.

See Also

`extractm` | `geoshow` | `mapshow` | `mlayers` | `updategeostruct`

Introduced before R2006a

dist2str

Convert numeric distance values into text

Syntax

```
str = dist2str(distin)
str = dist2str(dist,format)
str = dist2str(dist,format,units)
str = dist2str(dist,format,digits)
str = dist2str(dist,format,units,n)
```

Description

`str = dist2str(distin)` converts a numerical vector of distances in kilometers, `distin`, to a character array. The output character array is useful for the display of distances. The purpose of this function is to convert distance-valued variables into text suitable for map display.

`str = dist2str(dist,format)` specifies the notation to be used for the character array in `format`. If blank or 'none', the result is a simple numerical representation (no indicator for positive distances, minus signs for negative distances). The only other format is 'pm' (for *plus-minus*) prefixes a + for positive distances.

`str = dist2str(dist,format,units)` defines the units in which the input distances are supplied. Units must be one of the following: 'feet', 'kilometers', 'meters', 'nauticalmiles', 'statutemiles', 'degrees', or 'radians'. Note that statute miles are encoded as 'mi' in the character array, whereas in most Mapping Toolbox functions, 'mi' indicates international miles. If omitted or blank, 'kilometers' is assumed.

`str = dist2str(dist,format,digits)` or `str = dist2str(dist,format,units,n)` uses the input `n` to determine the number of decimal digits in the output matrix. If `n = -2`, the default, `dist2str` rounds to the nearest hundredth. If `n = 0`, `dist2str` rounds the output to the nearest integer. Note that this sign convention for `n` is opposite to the one used by the MATLAB `round` function.

Examples

Convert Vector of Numeric Values to Strings

Create a numeric vector.

```
d = [-3.7 2.95 87];
```

Convert the numeric values to strings.

```
str = dist2str(d, 'none', 'km')
```

```
str = 3x8 char array
    '-3.70 km'
     '2.95 km'
    '87.00 km'
```

Now change the units to nautical miles, add plus signs to positive values, and truncate to the tenths position.

```
str = dist2str(d, 'pm', 'nm', -1)
```

```
str = 3x8 char array
    '-3.7 nm'
    '+3.0 nm'
    '+87.0 nm'
```

See Also

[angl2str](#)

Introduced before R2006a

distance

Distance between points on sphere or ellipsoid

Syntax

```
[arclen,az] = distance(lat1,lon1,lat2,lon2)
[arclen,az] = distance(lat1,lon1,lat2,lon2,ellipsoid)
[arclen,az] = distance(pt1,pt2)
[arclen,az] = distance(pt1,pt2,ellipsoid)
[arclen,az] = distance( ____,units)
[arclen,az] = distance(track, ____)
```

Description

`[arclen,az] = distance(lat1,lon1,lat2,lon2)` computes the lengths, `arclen`, of the great circle arcs connecting pairs of points on the surface of a sphere. In each case, the shorter (minor) arc is assumed. The function can also compute the azimuths, `az`, of the second point in each pair with respect to the first (that is, the angle at which the arc crosses the meridian containing the first point).

`[arclen,az] = distance(lat1,lon1,lat2,lon2,ellipsoid)` computes geodesic arc length and azimuth assuming that the points lie on the reference ellipsoid defined by the input `ellipsoid`.

`[arclen,az] = distance(pt1,pt2)` accepts N -by-2 coordinate arrays of pairs of points, `pt1` and `pt2`, that store latitude coordinates in the first column and longitude coordinates in the second column.

This syntax is equivalent to `arclen = distance(pt1(:,1),pt1(:,2),pt2(:,1),pt2(:,2))`.

`[arclen,az] = distance(pt1,pt2,ellipsoid)` computes geodesic arc length and azimuth assuming that the points lie on the reference ellipsoid defined by the input `ellipsoid`.

`[arclen,az] = distance(____,units)` also specifies the angle units of the latitude and longitude coordinates for any of the preceding syntaxes.

`[arclen,az] = distance(track, ____,)` also specifies whether the track is a great circle/geodesic or a rhumb line arc, for any of the preceding syntaxes.

Examples

Find Difference in Distance Along Two Tracks

Using `pt1,pt2` notation, find the distance from Norfolk, Virginia (37°N, 76°W), to Cape St. Vincent, Portugal (37°N, 9°W), just outside the Straits of Gibraltar. The distance between these two points depends upon the *track* value selected.

```
arclen = distance('gc',[37,-76],[37,-9])
```

```
arclen =
```

```
52.3094
```

```
arclen = distance('rh',[37,-76],[37,-9])
```

```
arclen =
```

```
53.5086
```

The difference between these two tracks is 1.1992 degrees, or about 72 nautical miles. This represents about 2% of the total trip distance. The tradeoff is that at the cost of those 72 miles, the entire trip can be made on a rhumb line with a fixed course of 90°, due east, while in order to follow the shorter great circle path, the course must be changed continuously.

On a meridian and on the Equator, great circles and rhumb lines coincide, so the distances are the same. For example,

```
% Great circle distance
arclen = distance(37,-76,67,-76)
```

```
arclen =
```

```
30.0000
```

```
% Rhumb line distance
arclen = distance('rh',37,-76,67,-76)

arclen =

    30.0000
```

Input Arguments

lat1, lon1 — First set of latitude or longitude coordinates

numeric scalar | numeric array

First set of latitude or longitude coordinates, specified as a numeric scalar or numeric array. The coordinates are expressed in degrees unless units is specified as 'radians'.

Data Types: single | double

lat2, lon2 — Second set of latitude or longitude coordinates

numeric scalar | numeric array

Second set of latitude or longitude coordinates, specified as a numeric scalar or numeric array. The coordinates are expressed in degrees unless units is specified as 'radians'.

Data Types: single | double

pt1 — First set of point coordinates

N-by-2 numeric matrix

First set of point coordinates, specified as an *N*-by-2 numeric matrix. `pt1` is equivalent to `[lat1 lon1]` when `lat1` and `lon1` are column vectors.

Data Types: single | double

pt2 — Second set of point coordinates

N-by-2 numeric matrix

Second set of point coordinates, specified as an *N*-by-2 numeric matrix. `pt2` is equivalent to `[lat2 lon2]` when `lat2` and `lon2` are column vectors.

Data Types: single | double

ellipsoid — Reference ellipsoid

referenceSphere object | referenceEllipsoid object | oblateSpheroid object | two-element vector

Reference ellipsoid, specified as an referenceSphere, referenceEllipsoid, or oblateSpheroid object, or a two-element vector of the form [semimajor_axis eccentricity].

Example: referenceEllipsoid('GRS80')

Example: [6378.137 0.0818191910428158]

units — Angle units

'degrees' (default) | 'radians'

Angle units of the latitude and longitude coordinates, specified as 'degrees' or 'radians'.

Data Types: char

track — Track

'gc' (default) | 'rh'

Track, specified as one of the following character vectors.

- 'gc' — Great circle distances are computed on a sphere and geodesic distances are computed on an ellipsoid.
- 'rh' — Rhumb line distances are computed on either a sphere or ellipsoid.

Data Types: char

Output Arguments

arclen — Arc length

numeric scalar | numeric vector | numeric array

Arc length, returned as a numeric scalar or array of the same size as the input latitude and longitude arrays, lat1, lon1, lat2 and lon2. When coordinates are specified using coordinate arrays pt1 and pt2, then arclen is a numeric vector of length *N*.

- When ellipsoid is not specified, arclen is expressed in degrees or radians of arc, consistent with the value of units.

- When `ellipsoid` is specified, `arclen`, is expressed in the same length units as the semimajor axis of the ellipsoid.

Data Types: `double`

az — Azimuth

numeric scalar | numeric vector | numeric array

Azimuth of the second point in each pair with respect to the first, returned as a numeric scalar or array of the same size as the input latitude and longitude arrays, `lat1`, `lon1`, `lat2` and `lon2`. When coordinates are specified using coordinate arrays `pt1` and `pt2`, then `arclen` is a numeric vector of length N . `az` is measured clockwise from north.

Data Types: `single` | `double`

Tips

- The size of nonscalar latitude and longitude coordinates, `lat1`, `lon1`, `lat2`, and `lon2`, must be consistent. When given a combination of scalar and array inputs, the distance function automatically expands scalar inputs to match the size of the arrays.
- To express the output `arclen` as an arc length in either degrees or radians, omit the `ellipsoid` argument. This is possible only on a sphere. If `ellipsoid` is supplied, `arclen` is a distance expressed in the same units as the semimajor axis of the ellipsoid. Specify `ellipsoid` as `[R 0]` to compute `arclen` as a distance on a sphere of radius R , with `arclen` having the same units as R .

Algorithms

Distance calculations for geodesics degrade slowly with increasing distance and may break down for points that are nearly antipodal, as well as when both points are very close to the Equator. In addition, for calculations on an ellipsoid, there is a small but finite input space, consisting of pairs of locations in which both the points are nearly antipodal *and* both points fall close to (but not precisely on) the Equator. In this case, a warning is issued and both `arclen` and `az` are set to `NaN` for the “problem pairs.”

Alternatives

Distance between two points can be calculated in two ways. For great circles (on the sphere) and geodesics (on the ellipsoid), the distance is the shortest surface distance between two points. For rhumb lines, the distance is measured along the rhumb line passing through the two points, which is not, in general, the shortest surface distance between them.

When you need to compute both distance and azimuth for the same point pair(s), it is more efficient to do so with a single call to `distance`. That is, use

```
[arclen az] = distance(...);
```

rather than the slower

```
arclen = distance(...)  
az = azimuth(...)
```

See Also

Functions

`azimuth` | `elevation` | `reckon` | `track` | `track1` | `track2` | `trackg`

Objects

`oblateSpheroid` | `referenceEllipsoid` | `referenceSphere`

Topics

“Great Circles”

“Rhumb Lines”

“Small Circles”

Introduced before R2006a

distortcalc

Distortion parameters for map projections

Syntax

```
areascale = distortcalc(lat, long)
areascale = distortcalc(mstruct, lat, long)
[areascale, angdef, maxscale, minscale, merscale, parscale] =
distortcalc(...)
```

Description

`areascale = distortcalc(lat, long)` computes the area distortion for the current map projection at the specified geographic location. An area scale of 1 indicates no scale distortion. Latitude and longitude can be scalars, vectors, or matrices in the angle units of the defined map projection.

`areascale = distortcalc(mstruct, lat, long)` uses the projection defined in the map structure `mstruct`.

`[areascale, angdef, maxscale, minscale, merscale, parscale] = distortcalc(...)` computes the area scale, maximum angular deformation of right angles (in the angle units of the defined projection), the particular maximum and minimum scale distortions in any direction, and the particular scale along the meridian and parallel. You can also call `distortcalc` with fewer output arguments, in the order shown.

Background

Map projections inevitably introduce distortions in the shapes and sizes of objects as they are transformed from three-dimensional spherical coordinates to two-dimensional Cartesian coordinates. The amount and type of distortion vary between projections, over the projection, and with the selection of projection parameters such as standard parallels. This function allows a quantitative evaluation of distortion parameters.

Examples

At the equator, the Mercator projection is free of both area and angular distortion:

```
axesm mercator  
[areascale,angdef] = distortcalc(0,0)
```

```
areascale =  
    1.0000  
angdef =  
    8.5377e-007
```

At 60 degrees north, objects are shown at 400% of their true area. The projection is conformal, so angular distortion is still zero.

```
[areascale,angdef] = distortcalc(60,0)
```

```
areascale =  
    4.0000  
angdef =  
    4.9720e-004
```

Tips

This function uses a finite difference technique. The geographic coordinates are perturbed slightly in different directions and projected. A small amount of error is introduced by numerical computation of derivatives and the variation of map distortion parameters.

See Also

`mdistort` | `tissot`

Introduced before R2006a

distdim

Convert length units

Syntax

```
distOut = distdim(distIn, from, to)
distOut = distdim(distIn, from, to, radius)
distOut = distdim(distIn, from, to, sphere)
```

Note `distdim` has been replaced by `unitsratio`, but will be maintained for backward compatibility. See “Replacing `distdim`” on page 1-273 for details.

Description

`distOut = distdim(distIn, from, to)` converts `distIn` from the units specified by `from` to the units specified by `to`. `from` and `to` are case-insensitive, and may equal any of the following:

| | |
|--|------------------|
| 'meters' or 'm' | |
| 'feet' or 'ft' | U.S. survey feet |
| 'kilometers' or 'km' | |
| 'nauticalmiles' or 'nm' | |
| 'miles', 'statutemiles', 'mi', or 'sm' | Statute miles |
| 'degrees' or 'deg' | |
| 'radians' or 'rad' | |

If either `from` or `to` indicates angular units ('degrees' or 'radians'), the conversion to or from linear distance is made along a great circle arc on a sphere with a radius of 6371 km, the mean radius of the Earth.

`distOut = distdim(distIn, from, to, radius)` specifies the radius when one of the units, either `from` or `to`, indicates angular units. `distdim` uses a great circle arc on a

sphere of the given radius. The specified length units must apply to *radius* as well as to the input distance (when *from* indicates length) or output distance (when *to* indicates length). If neither *from* nor *to* indicates angular units, or if both do, then the value of *radius* is ignored.

`distOut = distdim(distIn, from, to, sphere)`, where either *from* or *to* indicates angular units, uses a great circle arc on a sphere approximating a body in the Solar System. *sphere* may be one of the following: 'sun', 'moon', 'mercury', 'venus', 'earth', 'mars', 'jupiter', 'saturn', 'uranus', 'neptune', or 'pluto', and is case-insensitive. If neither *to* nor *from* is angular, *sphere* is ignored.

Examples

Convert 100 kilometers to nautical miles:

```
distkm = 100
```

```
distkm =  
    100
```

```
distnm = distdim(distkm, 'kilometers', 'nauticalmiles')
```

```
distnm =  
    53.9957
```

A degree of arc length is about 60 nautical miles:

```
distnm = distdim(1, 'deg', 'nm')
```

```
distnm =  
    60.0405
```

This is not accidental. It is the original definition of the nautical mile. Naturally, this assumption does not hold on other planets:

```
distnm = distdim(1, 'deg', 'nm', 'mars')
```

```
distnm =  
    31.9474
```

Tips

Arc Lengths of Angles Not Constant

Distance is expressed in one of two general forms: as a linear measure in some unit (kilometers, miles, etc.) or as angular arc length (degrees or radians). While the use of linear units is generally understood, angular arc length is not always as clear. The conversion from angular units to linear units for the arc along any circle is the angle in radians multiplied by the radius of the circle. On the sphere, this means that radians of latitude are directly translatable to kilometers, say, by multiplying by the radius of the Earth in kilometers (about 6,371 km). However, the linear distance associated with radians of longitude changes with latitude; the radius in question is then not the radius of the Earth, but the (chord) radius of the small circle defining that parallel. The angle in radians or degrees associated with any distance is the arc length of a great circle passing through the points of interest. Therefore, the radius in question always refers to the radius of the relevant sphere, consistent with the `distance` function.

Exercise Caution with 'feet' and 'miles'

Exercise caution with 'feet' and 'miles'. `distdim` interprets 'feet' and 'ft' as U.S. survey feet, and does not support international feet at all. In contrast, `unitsratio` follows the opposite, and more standard approach, interpreting both 'feet' and 'ft' as international feet. `unitsratio` provides separate options, including 'surveyfeet' and 'sf', to indicate survey feet. By definition, one international foot is exactly 0.3048 meters and one U.S. survey foot is exactly 1200/3937 meters. For many applications, the difference is significant. Most projected coordinate systems use either the meter or the survey foot as a standard unit. International feet are less likely to be used, but do occur sometimes. Likewise, `distdim` interprets 'miles' and 'mi' as statute miles (also known as U.S. survey miles), and does not support international miles at all. By definition, one international mile is 5,280 international feet and one statute mile is 5,280 survey feet. You can evaluate:

```
unitsratio('millimeter','statute mile') - ...  
  unitsratio('millimeter','mile')
```

to see that the difference between a statute mile and an international mile is just over three millimeters. This may seem like a very small amount over the length of a single mile, but mixing up these units could result in a significant error over a sufficiently long baseline. Originally, the behavior of `distdim` with respect to 'miles' and 'mi' was

documented only indirectly, via the now-obsolete `unitstr` function. As with feet, `unitsratio` takes a more standard approach. `unitsratio` interprets 'miles' and 'mi' as international miles, and 'statute miles' and 'sm' as statute miles. (`unitsratio` accepts several other character vectors for each of these units; see the `unitsratio` help for further information.)

Replacing distdim

If both *from* and *to* are known at the time of coding, then you may be able to replace `distdim` with a direct conversion utility, as in the following examples:

| | |
|---|-------------------------------------|
| <code>distdim(dist, 'nm', 'km')</code> | <code>= nm2km(dist)</code> |
| <code>distdim(dist, 'sm', 'deg')</code> | <code>= sm2deg(dist)</code> |
| <code>distdim(dist, 'rad', 'km', 'moon')</code> | <code>= rad2km(dist, 'moon')</code> |

If there is no appropriate direct conversion utility, or you won't know the values of *from* and/or *to* until run time, you can generally replace

```
distdim(dist, FROM, TO)
```

with

```
unitsratio(TO, FROM) * dist
```

If you are using units of feet or miles, see the cautionary note above about how they are interpreted. For example, with `distIn` in meters and `distOut` in survey feet, `distOut = distdim(distIn, 'meters', 'feet')` should be replaced with `distOut = unitsratio('survey feet', 'meters') * distIn`. Saving a multiplicative factor computed with `unitsratio` and using it to convert in a separate step can make code cleaner and more efficient than using `distdim`. For example, replace

```
dist1_meters = distdim(dist1_nm, 'nm', 'meters');
dist2_meters = distdim(dist2_nm, 'nm', 'meters');
```

with

```
metersPerNM = unitsratio('meters', 'nm');
dist1_meters = metersPerNM * dist1_nm;
dist2_meters = metersPerNM * dist2_nm;
```

`unitsratio` does not perform great-circle conversion between units of length and angle, but it can be easily combined with other functions to do so. For example, to convert

degrees to meters along a great-circle arc on a sphere approximating the planet Mars, you could replace

```
distdim(dist, 'degrees', 'meters', 'mars')
```

with

```
unitsratio('meters','km') * deg2km(dist, 'mars')
```

See Also

deg2km | deg2nm | deg2sm | km2deg | km2nm | km2rad | km2sm | nm2deg | nm2km | nm2rad | nm2sm | rad2km | rad2nm | rad2sm | sm2deg | sm2km | sm2nm | sm2rad | unitsratio

Introduced before R2006a

dm2degrees

Convert degrees-minutes to degrees

Syntax

```
angleInDegrees = dms2degrees(DM)
```

Description

`angleInDegrees = dms2degrees(DM)` converts angles from degrees-minutes representation to values in degrees which may include a fractional part (sometimes called “decimal degrees”).

Examples

Convert Angle in Degree-Minutes to Degrees

```
dm = [ ...  
      30 44.78012; ...  
     -82 39.90825; ...  
       0 -17.12345; ...  
       0 14.82000];  
format long g  
angleInDegrees = dm2degrees(dm)
```

```
angleInDegrees = 4×1  
  
    30.74633533333333  
   -82.6651375  
  -0.2853908333333333  
     0.247
```

Input Arguments

DM — Angle in degrees-minutes representation

n-by-2 real-valued matrix

Angle in degrees-minutes representation, specified as an *n*-by-2 real-valued matrix. Each row specifies one angle, with the format [D M]:

- D contains the “degrees” element and must be integer-valued.
- M contains the “minutes” element and may have a fractional part. The absolute value of M must be less than 60.

For an angle that is positive (north latitude or east longitude) or equal to zero, all elements in the row must be nonnegative. For a negative angle (south latitude or west longitude), the first nonzero element in the row must be negative and the remaining value, if any, is nonnegative.

Output Arguments

angleInDegrees — Angle in degrees

n-element column vector

Angle in degrees, returned as an *n*-element column vector. The *k*th element corresponds to the *k*th row of DM.

Algorithms

For an input row with value [D M], with integer-valued D and real M, the output value will be

$$\text{SGN} * (\text{abs}(D) + \text{abs}(M)/60)$$

where SGN is 1 if D and M are both nonnegative and -1 if the first nonzero element of [D M] is negative. An error results if a nonzero D is followed by a negative M.

See Also

deg2rad | degrees2dm | dms2degrees | str2angle

Topics

“Angle Representations and Angular Units”

“Angles as Binary and Formatted Numbers”

Introduced in R2007a

dms2degrees

Convert degrees-minutes-seconds to degrees

Syntax

```
angleInDegrees = dms2degrees(DMS)
```

Description

`angleInDegrees = dms2degrees(DMS)` converts angles from degrees-minutes-seconds representation to values in degrees which may include a fractional part (sometimes called “decimal degrees”).

Examples

Convert Angle in Degree-Minute-Seconds to Degrees

```
dms = [ ...  
      30 50 44.78012; ...  
     -82  2 39.90825; ...  
      0 -30 17.12345; ...  
      0  0 14.82000];  
format long g  
angleInDegrees = dms2degrees(dms)
```

```
angleInDegrees = 4×1  
  
    30.8457722555556  
   -82.0444189583333  
   -0.504756513888889  
    0.00411666666666667
```


Input Arguments

DMS — Angle in degrees-minutes-seconds representation

n-by-3 real-valued matrix

Angle in degrees-minutes-seconds representation, specified as an *n*-by-3 real-valued matrix. Each row specifies one angle, with the format [D M S]:

- D contains the “degrees” element and must be integer-valued.
- M contains the “minutes” element and must be integer-valued. The absolute value of M must be less than 60.
- S contains the “seconds” element and may have a fractional part. The absolute value of S must be less than 60.

For an angle that is positive (north latitude or east longitude) or equal to zero, all elements in the row must be nonnegative. For a negative angle (south latitude or west longitude), the first nonzero element in the row must be negative and the remaining values are nonnegative.

Output Arguments

angleInDegrees — Angle in degrees

n-element column vector

Angle in degrees, returned as an *n*-element column vector. The *k*th element corresponds to the *k*th row of DMS.

Algorithms

For an input row with value [D M S], the output value will be

$$\text{SGN} * (\text{abs}(D) + \text{abs}(M)/60 + \text{abs}(S)/3600)$$

where SGN is 1 if D, M, and S are all nonnegative and -1 if the first nonzero element of [D M S] is negative. An error results if a nonzero element is followed by a negative element.

See Also

deg2rad | degrees2dm | dm2degrees | str2angle

Topics

“Angle Representations and Angular Units”

“Angles as Binary and Formatted Numbers”

Introduced in R2007a

double

Package: map.geotiff

Convert TIFF tag property values to row vector of doubles

Syntax

```
tiffTagValue = double(rpctag)
```

Description

`tiffTagValue = double(rpctag)` returns a 92-element row vector of class `double`, representing the values of the TIFF tag. This is the format required to write the property values to a TIFF file.

Examples

Convert RPCCoefficientTag Properties to 92-Element Vector

Create an `RPCCoefficientTag` object and view the object summary display.

```
rpctag = map.geotiff.RPCCoefficientTag
```

```
rpctag =  
  RPCCoefficientTag with properties:  
  
      BiasErrorInMeters: -1  
  RandomErrorInMeters: -1  
           LineOffset: 0  
        SampleOffset: 0  
  GeodeticLatitudeOffset: 0  
  GeodeticLongitudeOffset: 0  
  GeodeticHeightOffset: 0  
           LineScale: 1  
        SampleScale: 1
```

```
GeodeticLatitudeScale: 1
GeodeticLongitudeScale: 1
GeodeticHeightScale: 1
LineNumeratorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
LineDenominatorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
SampleNumeratorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
SampleDenominatorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
```

Call the `RPCCoefficientTag` class method `double` to convert the object into a vector of doubles. View the result.

```
tifftagvalues = double(rpctag)
```

```
tifftagvalues = 1×92
```

```
-1 -1 0 0 0 0 0 1 1 1 1 1 0 0
```

Input Arguments

rpctag — Rational Polynomial Coefficients (RPC) TIFF tag property values

`RPCCoefficientTag` object

Rational Polynomial Coefficients (RPC) TIFF tag property values, specified as an `RPCCoefficientTag` object.

Example: `tifftagvalues = double(rpctag);`

Output Arguments

tiffTagValue — Rational Polynomial Coefficients (RPC) TIFF tag property values

92-element vector

Rational Polynomial Coefficients (RPC) TIFF tag property values, returned as 92-element vector of class `double`.

See Also

`RPCCoefficientTag` | `geotiffinfo` | `geotiffwrite`

Introduced in R2015b

dreckon

Dead reckoning positions for track

Syntax

```
[drlat,drlong,drtime] = dreckon(waypoints,time,speed)
[drlat,drlong,drtime] = dreckon (waypoints,time,speed,spdtimes)
```

Description

[drlat,drlong,drtime] = dreckon(waypoints,time,speed) returns the positions and times of required dead reckoning (DR) points for the input track that starts at the input time. The track should be in navigational track format (two columns, latitude then longitude, in order of traversal). These waypoints are the starting and ending points of each leg of the track. There is one fewer track leg than waypoints, as the last point included is the end of the track. In navigation, the first waypoint would be a navigational fix, taken at `time`. The `speed` input can be a scalar, in which case a constant speed is used throughout, or it can be a vector in which one speed is given for each track leg (that is, speed changes coincide with course changes).

[drlat,drlong,drtime] = dreckon (waypoints,time,speed,spdtimes) allows speed changes to occur independent of course changes. The elements of the `speed` vector must have a one-to-one correspondence with the elements of the `spdtimes` vector. This latter variable consists of the time interval after `time` at which each speed order *ends*. For example, if `time` is 6.75, and the first element of `spdtimes` is 1.35, then the first speed element is in effect from 6.75 to 8.1 hours. When this syntax is used, the last output DR is the *earlier* of the final `spdtimes` time or the final waypoints point.

Background

This is a navigational function. It assumes that all latitudes and longitudes are in degrees, all distances are in nautical miles, all times are in hours, and all speeds are in knots, that is, nautical miles per hour.

Dead reckoning is an estimation of position at various times based on courses, speeds, and times elapsed from the last certain position, or fix. In navigational practice, a dead reckoning position, or DR, must be plotted at every course change, every speed change, and at every hour, on the hour. Navigators also DR at other times that are not relevant to this function.

Often in practice, when two events occur that require DRs within a very short time, only one DR is generated. This function mimics that practice by setting a tolerance of 3 minutes (0.05 hours). No two DRs will fall closer than that.

Refer to “Navigation” in the *Mapping Toolbox Guide* for further information.

Examples

Assume that a navigator gets a fix at noon, 1200Z, which is (10.3°N, 34.67°W). He's in a hurry to make a 1330Z rendezvous with another ship at (9.9°N, 34.5°W), so he plans on a speed of 25 knots. After the rendezvous, both ships head for (0°, 37°W). The engineer wants to take an engine off line for maintenance at 1430Z, so at that time, speed must be reduced to 15 knots. At 1530Z, the maintenance will be done. Determine the DR points up to the end of the maintenance.

```
waypoints = [10.1 -34.6; 9.9 -34.5; 0 -37]

waypoints =
    10.1000  -34.6000      % Fix at noon
     9.9000  -34.5000      % Rendezvous point
     0      -37.0000      % Ultimate destination

speed = [25; 15];
spdtimes = [2.5; 3.5];      % Elapsed times after fix
noon = 12;
[drlat,drlong,dertime] = dreckon(waypoints,noon,speed,spdtimes);
[drlat,drlong,dertime]

ans =
    9.8999  -34.4999   12.5354      % Course change at waypoint
    9.7121  -34.5478   13.0000      % On the hour
    9.3080  -34.6508   14.0000      % On the hour
    9.1060  -34.7022   14.5000      % Speed change to 15 kts
    8.9847  -34.7330   15.0000      % On the hour
    8.8635  -34.7639   15.5000      % Stop at final spdtime, last
                                     % waypoint has not been reached
```

See Also

[legs](#) | [navfix](#) | [track](#)

Introduced before R2006a

driftcorr

Heading to correct for wind or current drift

Syntax

```
heading = driftcorr(course,airspeed,windfrom,windspeed)
[heading,groundspeed,windcorrangle] = driftcorr(...)
```

Description

`heading = driftcorr(course,airspeed,windfrom,windspeed)` computes the heading that corrects for drift due to wind (for aircraft) or current (for watercraft). `course` is the desired direction of movement (in degrees), `airspeed` is the speed of the vehicle relative to the moving air or water mass, `windfrom` is the direction facing into the wind or current (in degrees), and `windspeed` is the speed of the wind or current (in the same units as `airspeed`).

`[heading,groundspeed,windcorrangle] = driftcorr(...)` also returns the ground speed and wind correction angle. The wind correction angle is positive to the right, and negative to the left.

Examples

An aircraft cruising at a speed of 160 knots plans to fly to an airport due north of its current position. If the wind is blowing from 310 degrees at 45 knots, what heading should the aircraft fly to remain on course?

```
course=0; airspeed=160;windfrom=310; windspeed = 45;
[heading,groundspeed,windcorrangle] =
driftcorr(course,airspeed,windfrom,windspeed)
```

```
heading =
```

```
347.56
```

groundspeed =

127.32

windcorrangle =

-12.442

The required heading is 348 degrees, which amounts to a wind correction angle of 12 degrees to the left of course. The headwind component reduces the aircraft's ground speed to 127 knots.

See Also

driftvel

Introduced before R2006a

driftvel

Wind or current from heading, course, and speeds

Syntax

```
[windfrom,windspeed] = driftvel  
(course,groundspeed,heading,airspeed)
```

Description

```
[windfrom,windspeed] = driftvel  
(course,groundspeed,heading,airspeed)
```

 computes the wind (for aircraft) or current (for watercraft) from course, heading, and speeds. `course` and `groundspeed` are the direction and speed of movement relative to the ground (in degrees), `heading` is the direction in which the vehicle is steered, and `airspeed` is the speed of the vehicle relative to the air mass or water. The output `windfrom` is the direction facing into the wind or current (in degrees), and `windspeed` is the speed of the wind or current (in the same units as `airspeed` and `groundspeed`).

Examples

An aircraft is cruising at a true air speed of 160 knots and a heading of 10 degrees. From the Global Positioning System (GPS) receiver, the pilot determines that the aircraft is progressing over the ground at 155 knots in a northerly direction. What is the wind aloft?

```
course = 0; groundspeed = 155; heading = 10; airspeed = 160;  
[windfrom,windspeed] =  
driftvel(course,groundspeed,heading,airspeed)
```

```
windfrom =  
    84.717
```

```
windspeed =  
    27.902
```

The wind is blowing from the right, 085 degrees at 28 knots.

See Also

driftcorr

Introduced before R2006a

dted

Read U.S. Department of Defense Digital Terrain Elevation Data (DTED)

Syntax

```
[Z, refvec] = dted
[Z, refvec] = dted(filename)
[Z, refvec] = dted(filename, samplefactor)
[Z, refvec] = dted(filename, samplefactor, latlim, lonlim)
[Z, refvec] = dted(foldername, samplefactor, latlim, lonlim)
[Z, refvec, UHL, DSI, ACC] = dted(...)
```

Description

`[Z, refvec] = dted` returns all of the elevation data in a DTED file as a regular data grid, `Z`, with elevations in meters. The file is selected interactively. This function reads the DTED elevation files, which generally have filenames ending in `.dtN`, where `N` is `0,1,2,3,...`. `refvec` is the associated three-element referencing vector that geolocates `Z`.

`[Z, refvec] = dted(filename)` returns all of the elevation data in the specified DTED file. The file must be found on the MATLAB path. If not found, the file may be selected interactively.

`[Z, refvec] = dted(filename, samplefactor)` subsamples data from the specified DTED file. `samplefactor` is a scalar integer. When `samplefactor` is 1 (the default), DTED reads the data at its full resolution. When `samplefactor` is an integer `n` greater than one, every `n`th point is read.

`[Z, refvec] = dted(filename, samplefactor, latlim, lonlim)` reads the data for the part of the DTED file within the latitude and longitude limits. The limits must be two-element vectors in units of degrees.

`[Z, refvec] = dted(foldername, samplefactor, latlim, lonlim)` reads and concatenates data from multiple files within a DTED CD-ROM or folder structure. The `foldername` input is a string scalar or character vector with the name of a folder containing the DTED folder. Within the DTED folder are subfolders for each degree of

longitude, each of which contain files for each degree of latitude. For DTED CD-ROMs, `foldername` is the device name of the CD-ROM drive.

`[Z, refvec, UHL, DSI, ACC] = dted(...)` returns structures containing the DTED User Header Label (UHL), Data Set Identification (DSI) and Accuracy metadata records.

Background

The U. S. Department of Defense, through the National Geospatial Intelligence Agency, produces several kinds of digital cartographic data. One is digital elevation data, in a series called DTED, for Defense Digital Terrain Elevation Data. The data is available as 1-by-1 degree quadrangles at horizontal resolutions ranging from about 1 kilometer to 1 meter. The lowest resolution data is available to the public. Certain higher resolution data is restricted to the U.S. Department of Defense and its contractors.

DTED Level 0 files have 121-by-121 points. DTED Level 1 files have 1201-by-1201. The edges of adjacent tiles have redundant records. Maps extend a half a cell outside the requested map limits. The 1 kilometer data and some higher-resolution data is available online, as are product specifications and documentation. DTED files are binary. No line ending conversion or byte-swapping is required when downloading a DTED file.

Examples

Read Digital Terrain Elevation Data (DTED)

This example shows how to read Digital Terrain Elevation Data (DTED). To run this example, you must have a DTED file. For details on locating DTED for download over the Internet, see “Find Geospatial Data Online”.

Read the DTED file.

```
[Z,refvec] = dted('n38.dt0');
```

Read Digital Terrain Elevation Data (DTED) Specifying Sample Factor and Latitude and Longitude

This example shows how to read Digital Terrain Elevation Data (DTED), specifying the sample factor and latitude and longitude. To run this example, you must have a DTED file.

For details on locating DTED for download over the Internet, see “Find Geospatial Data Online”.

Read the DTED file, specifying sample factor along with latitude and longitude. The example returns structures containing the DTED User Header Label (UHL), Data Set Identification (DSI) and Accuracy metadata records.

```
[Z,refvec,UHL,DSI,ACC] = dted('n38.dt0',1,[38.5 38.8],...
    [-76.8 -76.6]);
```

Read Digital Terrain Elevation Data (DTED) Specifying Folder Name

This example shows how to read Digital Terrain Elevation Data (DTED) specifying a folder name. To run this example, you must have DTED files. For details on locating DTED for download over the Internet, see “Find Geospatial Data Online”.

Read the DTED files in the folder specified. The example returns structures containing the DTED User Header Label (UHL), Data Set Identification (DSI) and Accuracy metadata records.

```
[Z,refvec,UHL,DSI,ACC] = dted('f:',1,[38.5 38.8],...
    [-76.8 -76.6]);
```

Tips

Latitude-Dependent Sampling

In DTED files north of 50° North and south of 50° South, where the meridians have converged significantly relative to the equator, the longitude sampling interval is reduced to half of the latitude sampling interval. In order to retain square output cells, this function reduces the latitude sampling to match the longitude sampling. For example, it will return a 121-by-121 elevation grid for a DTED file covering from 49 to 50 degrees north, but a 61-by-61 grid for a file covering from 50 to 51 degrees north. When you supply a folder name instead of a file name, and `latlim` spans either 50° North or 50° South, an error results.

Snapping Latitude and Longitude Limits

If you call `dted` specifying arbitrary latitude-longitude limits for a region of interest, the grid and referencing vector returned will not exactly honor the limits you specified unless they fall precisely on grid cell boundaries. Because grid cells are discrete and cannot be arbitrarily divided, the data grid returned will include all areas between your latitude-longitude limits and the next row or column of cells, potentially in all four directions.

Data Sources and Information

DTED files contain digital elevation maps covering 1-by-1-degree quadrangles at horizontal resolutions ranging from about 1 kilometer to 1 meter. For details on locating DTED for download over the Internet, see “Find Geospatial Data Online”.

Null Data Values

Some DTED Level 1 and higher data tiles contain null data cells, coded with value -32767. When encountered, these null data values are converted to NaN.

Nonconforming Data Encoding

DTED files from some sources may depart from the specification by using two's complement encoding for binary elevation files instead of “sign-bit” encoding. This difference affects the decoding of negative values, and incorrect decoding usually leads to nonsensical elevations.

Thus, if the DTED function determines that all the (nonnull) negative values in a file would otherwise be less than -12,000 meters, it issues a warning and assumes two's complement encoding.

See Also

`etopo` | `gtopo30` | `tbase` | `usgsdem`

Introduced before R2006a

dteds

DTED filenames for latitude-longitude quadrangle

Syntax

```
fname = dteds(latlim,lonlim)
fname = dteds(latlim,lonlim,level)
```

Description

`fname = dteds(latlim,lonlim)` returns Level 0 DTED file names (folder and name) required to cover the geographic region specified by `latlim` and `lonlim`. This function constructs the file names for a given geographic region based on the file-naming convention established by the Defense Digital Terrain Elevation Data (DTED) database.

`fname = dteds(latlim,lonlim,level)` controls the level for which the file names are generated. Valid inputs for the `level` of the DTED files include 0, 1, or 2.

Background

The U. S. Department of Defense produces several kinds of digital cartographic data. One is digital elevation data, in a series called DTED, for Defense Digital Terrain Elevation Data. The data is available as 1-by-1 degree quadrangles at horizontal resolutions ranging from about 1 kilometer to 1 meter. The lowest resolution data is available to the public. Higher resolution data is restricted to the U.S. Department of Defense and its contractors.

Determining the files needed to cover a particular region requires knowledge of the DTED database naming conventions. This function constructs the file names for a given geographic region based on these conventions. For more information, see “Determine What Elevation Data Exists for a Region”.

Examples

Which files are needed for Cape Cod?

```
latlim = [ 41.15 42.22]; lonlim = [-70.94 -69.68];  
dteds(latlim,lonlim,1)
```

```
ans =  
    '\DTED\W071\N41.dt1'  
    '\DTED\W070\N41.dt1'  
    '\DTED\W071\N42.dt1'  
    '\DTED\W070\N42.dt1'
```

See Also

dted

Topics

“Determine What Elevation Data Exists for a Region”

Introduced before R2006a

earthRadius

Mean radius of planet Earth

Syntax

```
R = earthRadius
R = earthRadius(lengthUnit)
```

Description

`R = earthRadius` returns the scalar value 6371000, the mean radius of the Earth in meters.

`R = earthRadius(lengthUnit)` returns the mean radius of the Earth using the specified unit of length. The `lengthUnit` input may be any value accepted by the `validateLengthUnit` function.

Examples

Retrieve the mean radius of the Earth, using several units.

```
earthRadius           % Returns 6371000
```

```
earthRadius('meters') % Returns 6371000
```

```
earthRadius('km')    % Returns 6371
```

See Also

`unitsratio` | `validateLengthUnit`

Introduced in R2010b

eastof

Wrap longitudes to values east of specified meridian

Note The `eastof` function is obsolete and will be removed in a future release of Mapping Toolbox software. Replace it with the following calls, which are also more efficient:

```
eastof(lon,meridian,'degrees') ==> meridian+mod(lon-meridian,360)
```

```
eastof(lon,meridian,'radians') ==> meridian+mod(lon-meridian,2*pi)
```

Syntax

```
lonWrapped = eastof(lon,meridian)
```

```
lonWrapped = eastof(lon,meridian,angleunits)
```

Description

`lonWrapped = eastof(lon,meridian)` wraps angles in `lon` to values in the interval `[meridian meridian+360)`. `lon` is a scalar longitude or vector of longitude values. All inputs and outputs are in degrees.

`lonWrapped = eastof(lon,meridian,angleunits)` where the character vector `angleunits` specifies the input and output units. `angleunits` can be either `'degrees'` or `'radians'`. It may be abbreviated and is case-insensitive. If `angleunits` is `'radians'`, the input is wrapped to the interval `[meridian meridian+2*pi)`.

Introduced before R2006a

ecc2flat

Flattening of ellipse from eccentricity

Note Support for nonscalar input, including the syntax `f = ecc2flat(ellipsoid)`, will be removed in a future release.

Syntax

```
f = ecc2flat(ecc)
f = ecc2flat(ellipsoid)
```

Description

`f = ecc2flat(ecc)` computes the flattening of an ellipse (or ellipsoid of revolution) given its eccentricity `ecc`. Except when the input has 2 columns (or is a row vector), each element is assumed to be an eccentricity and the output `f` has the same size as `ecc`.

`f = ecc2flat(ellipsoid)`, where `ellipsoid` has two columns (or is a row vector), assumes that the eccentricity is in the second column, and a column vector is returned.

See Also

`ecc2n` | `flat2ecc` | `majaxis` | `minaxis`

Introduced before R2006a

ecc2n

Third flattening of ellipse from eccentricity

Note Support for nonscalar input, including the syntax `n = ecc2n(ellipsoid)`, will be removed in a future release.

Syntax

```
n = ecc2n(ecc)
n = ecc2n(ellipsoid)
```

Description

`n = ecc2n(ecc)` computes the parameter n (the "third flattening") of an ellipse (or ellipsoid of revolution) given its eccentricity `ecc`. n is defined as $(a-b)/(a+b)$, where a is the semimajor axis and b is the semiminor axis. Except when the input has 2 columns (or is a row vector), each element is assumed to be an eccentricity and the output n has the same size as `ecc`.

`n = ecc2n(ellipsoid)`, where `ellipsoid` has two columns (or is a row vector), assumes that the eccentricity is in the second column, and a column vector is returned.

See Also

`ecc2flat` | `majaxis` | `minaxis` | `n2ecc`

Introduced before R2006a

ecef2aer

Geocentric ECEF to local spherical AER

Syntax

```
[az,elev,slantRange] = ecef2aer(X,Y,Z,lat0,lon0,h0,spheroid)  
[ ___ ] = ecef2aer( ___ ,angleUnit)
```

Description

[az,elev,slantRange] = ecef2aer(X,Y,Z,lat0,lon0,h0,spheroid) returns coordinates in a local spherical system corresponding to coordinates X, Y, Z in an Earth-Centered Earth-Fixed (ECEF) spheroid-centric Cartesian system. Any of the first six numeric input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

[___] = ecef2aer(___ ,angleUnit) adds angleUnit which specifies the units of inputs lat0, lon0, and outputs az, elev.

Input Arguments

X — ECEF x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the spheroid-centric ECEF system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the LengthUnit property of the spheroid object.

Data Types: single | double

Y — ECEF y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the spheroid-centric ECEF system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the spheroid object.

Data Types: `single` | `double`

Z — ECEF y-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid object.

lat0 — Geodetic latitude of local origin

scalar value | vector | matrix | N-D array

Geodetic latitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lat0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon0 — Longitude of local origin

scalar value | vector | matrix | N-D array

Longitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lon0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

h0 — Ellipsoidal height of local origin

scalar value | vector | matrix | N-D array

Ellipsoidal height of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `h0` is scalar, but it need not be. (It may refer to a moving platform, for example). Units are determined by the `LengthUnit` property of the spheroid input.

Data Types: `single` | `double`

spheroid — Reference spheroid

referenceEllipsoid | oblateSpheroid | referenceSphere

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. To create a spheroid object, use the creation function specific to the object, or the `wgs84Ellipsoid` function.

Example: `spheroid = referenceEllipsoid('GRS 80');`

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: `char` | `string`

Output Arguments

az — Azimuth angles

scalar value | vector | matrix | N-D array

Azimuth angles in the local spherical system, returned as a scalar value, vector, matrix, or N-D array. Azimuths are measured clockwise from north. Units are determined by the input argument `angleUnit`, if supplied; values are in degrees, otherwise. When in degrees, they lie in the half-open interval [0 360).

elev — Elevation angles

scalar value | vector | matrix | N-D array

Elevation angles in the local spherical system, returned as a scalar value, vector, matrix, or N-D array. Elevations are with respect to a plane perpendicular to the spheroid surface normal. Units determined by the input argument `angleUnit`, if supplied; values are in degrees, otherwise. When in degrees, they lie in the closed interval [-90 90].

sLantRange — Distances from local origin

scalar value | vector | matrix | N-D array

Distances from origin in the local spherical system, returned as a scalar value, vector, matrix, or N-D array. The straight-line, 3-D Cartesian distance is computed. Units are determined by the `LengthUnit` property of the `spheroid` input.

See Also

[aer2ecef](#) | [ecef2enu](#) | [ecef2ned](#) | [geodetic2aer](#)

Introduced in R2012b

ecef2enu

Geocentric ECEF to local Cartesian ENU

Syntax

```
[xEast,yNorth,zUp] = ecef2enu(X,Y,Z,lat0,lon0,h0,spheroid)  
[ ___ ] = ecef2enu( ___ ,angleUnit)
```

Description

[xEast,yNorth,zUp] = ecef2enu(X,Y,Z,lat0,lon0,h0,spheroid) returns coordinates in a local east-north-up (ENU) Cartesian system corresponding to coordinates X, Y, Z in an Earth-Centered Earth-Fixed (ECEF) spheroid-centric Cartesian system. Any of the first six numeric input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

[___] = ecef2enu(___ ,angleUnit) adds angleUnit which specifies the units of inputs, lat0, and lon0.

Input Arguments

X — ECEF x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the spheroid-centric ECEF system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the LengthUnit property of the spheroid object.

Data Types: single | double

Y — ECEF y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the spheroid-centric ECEF system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the spheroid object.

Data Types: `single` | `double`

Z — ECEF y-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid object.

lat0 — Geodetic latitude of local origin

scalar value | vector | matrix | N-D array

Geodetic latitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lat0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon0 — Longitude of local origin

scalar value | vector | matrix | N-D array

Longitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lon0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

h0 — Ellipsoidal height of local origin

scalar value | vector | matrix | N-D array

Ellipsoidal height of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `h0` is scalar, but it need not be. (It may refer to a moving platform, for example). Units are determined by the `LengthUnit` property of the spheroid input.

Data Types: `single` | `double`

spheroid — Reference spheroid

referenceEllipsoid | oblateSpheroid | referenceSphere

Reference spheroid, specified as a referenceEllipsoid, oblateSpheroid, or referenceSphere object. To create a spheroid object, use the creation function specific to the object, or the wgs84Ellipsoid function.

Example: spheroid = referenceEllipsoid('GRS 80');

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: char | string

Output Arguments

xEast — Local ENU x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the local ENU system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the LengthUnit property of the spheroid input.

yNorth — Local ENU y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the local ENU system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the LengthUnit property of the spheroid input.

zUp — Local ENU z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the local ENU system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the LengthUnit property of the spheroid input.

See Also

[ecef2aer](#) | [ecef2ned](#) | [enu2ecef](#) | [geodetic2enu](#)

Introduced in R2012b

ecef2enuv

Rotate vector from geocentric ECEF to local ENU

Syntax

```
[uEast,vNorth,wUp] = ecef2enuv(U,V,W,lat0,lon0)
[ ___ ] = ecef2enuv( ___ ,angleUnit)
```

Description

[uEast,vNorth,wUp] = ecef2enuv(U,V,W,lat0,lon0) returns Cartesian 3-vector components in a local east-north-up (ENU) system corresponding to the 3-vector with components U, V, W in an Earth-Centered Earth-Fixed (ECEF) spheroid-centric Cartesian system. Any of the five numerical input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

[___] = ecef2enuv(___ ,angleUnit) adds angleUnit which specifies the units of inputs lat0 and lon0.

Input Arguments

U — Vector x-components in ECEF system

scalar value | vector | matrix | N-D array

x-components of one or more Cartesian vectors in the spheroid-centric ECEF system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: single | double

V — Vector y-components in ECEF system

scalar value | vector | matrix | N-D array

y-components of one or more Cartesian vectors in the spheroid-centric ECEF system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: single | double

W — Vector z-components in ECEF system

scalar value | vector | matrix | N-D array

z-components of one or more Cartesian vectors in the spheroid-centric ECEF system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: `single` | `double`

lat0 — Geodetic latitude of local origin

scalar value | vector | matrix | N-D array

Geodetic latitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lat0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon0 — Longitude of local origin

scalar value | vector | matrix | N-D array

Longitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lon0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: `char` | `string`

Output Arguments

uEast — Vector x-components in ENU system

scalar value | vector | matrix | N-D array

x-components of one or more Cartesian vectors in the local ENU system, returned as a scalar value, vector, matrix, or N-D array.

vNorth — Vector y-components in ENU system

scalar value | vector | matrix | N-D array

y-components of one or more Cartesian vectors in the local ENU system, returned as a scalar value, vector, matrix, or N-D array.

wUp — Vector z-components in ENU system

scalar value | vector | matrix | N-D array

z-components of one or more Cartesian vectors in the local ENU system, returned as a scalar value, vector, matrix, or N-D array.

See Also

ecef2enu | ecef2nedv | enu2ecefv

Introduced in R2012b

ecef2geodetic

Transform geocentric (ECEF) to geodetic coordinates

Syntax

```
[lat,lon,h] = ecef2geodetic(spheroid,X,Y,Z)
[lat,lon,h] = ecef2geodetic( ____,angleUnit)

[lat,lon,h] = geodetic2ecef(X,Y,Z,spheroid)
```

Description

[lat,lon,h] = ecef2geodetic(spheroid,X,Y,Z) transforms point locations in geocentric Earth-Centered Earth-Fixed (ECEF) Cartesian coordinates, stored in the coordinate arrays X, Y, and Z, to geodetic coordinates `lat` (geodetic latitude), `lon` (longitude), and `h` (ellipsoidal height). The geodetic coordinates refer to the reference body specified by the spheroid object, `spheroid`.

[lat,lon,h] = ecef2geodetic(____,angleUnit) uses the character vector `angleUnit`, which matches either 'degrees' or 'radians', to specify the units of the latitude and longitude coordinates.

[lat,lon,h] = geodetic2ecef(X,Y,Z,spheroid) This syntax is supported but not recommended. This syntax returns `lat` and `lon` in radians. `spheroid` can be either a spheroid or an ellipsoid vector of the form: [semimajor_axis, eccentricity]. X, Y, and Z must use the same units as the semimajor axis. In this case, H must use the same units as the semimajor axis.

Examples

Convert Geocentric Coordinates to Geodetic Coordinates

Convert the geocentric Earth-Centered Earth-Fixed (ECEF) Cartesian coordinates for Paris, France into geodetic coordinates (latitude,longitude).

```
x = 4.2010e+06;  
y = 1.7246e+05;  
z = 4.7801e+06;  
wgs84 = wgs84Ellipsoid('meters');  
[lat,lon,h] = ecef2geodetic(wgs84,x,y,z)  
  
lat = 48.8562  
lon = 2.3508  
h = 67.3700
```

Input Arguments

spheroid — Reference spheroid

referenceEllipsoid | oblateSpheroid | referenceSphere

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. To create a spheroid object, use the creation function specific to the object, or the `wgs84Ellipsoid` function.

Example: `spheroid = referenceEllipsoid('GRS 80');`

X — ECEF x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the spheroid-centric ECEF system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the spheroid object.

Data Types: `single` | `double`

Y — ECEF y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the spheroid-centric ECEF system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the spheroid object.

Data Types: `single` | `double`

Z — ECEF z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the `spheroid` object.

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: char | string

Output Arguments

lat — Geodetic latitudes

scalar value | vector | matrix | N-D array

Geodetic latitudes of one or more points, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the input argument `angleUnit`, if supplied; values are in degrees, otherwise. When in degrees, they lie in the closed interval [-90 90].

lon — Longitudes

scalar value | vector | matrix | N-D array

Longitudes of one or more points, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the input argument `angleUnit`, if supplied; values are in degrees, otherwise. When in degrees, they lie in the interval [-180 180].

h — Ellipsoidal heights

scalar value | vector | matrix | N-D array

Ellipsoidal heights of one or more points, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the `spheroid` object

Tips

- The geocentric Cartesian (ECEF) coordinate system is fixed with respect to the Earth, with its origin at the center of the spheroid and its positive X-, Y-, and Z axes intersecting the surface at the following points:

| | Latitude | Longitude | Notes |
|--------|-----------------|------------------|-------------------------------|
| X-axis | 0 | 0 | Equator at the Prime Meridian |
| Y-axis | 0 | 90 | Equator at 90-degrees East |
| Z-zxis | 90 | 0 | North Pole |

See Also

[ecef0ffset](#) | [geodetic2ecef](#) | [oblateSpheroid](#) | [referenceEllipsoid](#) | [referenceSphere](#)

Introduced in R2012b

ecef2lv

Convert geocentric (ECEF) to local vertical coordinates

Note ecef2lv will be removed in a future release. Use ecef2enu instead. In ecef2enu, the latitude and longitude of the local origin are in degrees by default, so the optional angleUnit input should be included, with the value 'radians'.

Syntax

```
[xl,yl,zl] = ecef2lv(x,y,z,phi0,lambda0,h0,ellipsoid)
```

Description

[xl,yl,zl] = ecef2lv(x,y,z,phi0,lambda0,h0,ellipsoid) converts geocentric point locations specified by the coordinate arrays x, y, and z to the local vertical coordinate system, with its origin at geodetic latitude phi0, longitude lambda0, and ellipsoidal height h0. The arrays x, y, and z may be of any shape, as long as they all match in size. phi0, lambda0, and h0 must be scalars. ellipsoid is a referenceEllipsoid (oblateSpheroid) object, a referenceSphere object, or a vector of the form [semimajor axis, eccentricity]. x, y, z, and h0 must have the same length units as the semimajor axis. phi0 and lambda0 must be in radians. The output coordinate arrays, xl, yl, and zl are the local vertical coordinates of the input points. They have the same size as x, y, and z and have the same length units as the semimajor axis.

In the local vertical Cartesian system defined by phi0, lambda0, h0, and ellipsoid, the xl axis is parallel to the plane tangent to the ellipsoid at (phi0,lambda0) and points due east. The yl axis is parallel to the same plane and points due north. The zl axis is normal to the ellipsoid at (phi0,lambda0) and points outward into space. The local vertical system is sometimes referred to as east-north-up or ENU.

Definitions

Local Vertical System

In the local vertical Cartesian system defined by ϕ_0 , λ_0 , h_0 , and `ellipsoid`, the x_l axis is parallel to the plane tangent to the ellipsoid at (ϕ_0, λ_0) and points due east. The y_l axis is parallel to the same plane and points due north. The z_l axis is normal to the ellipsoid at (ϕ_0, λ_0) and points outward into space. The local vertical system is sometimes referred to as East-North-Up or ENU.

Geocentric System

The geocentric Cartesian coordinate system, also known as Earth-Centered, Earth-Fixed (ECEF), is fixed with respect to the Earth, with its origin at the center of the spheroid and its positive X-, Y-, and Z axes intersecting the surface at the following points:

| | Latitude | Longitude | Notes |
|--------|----------|-----------|-------------------------------|
| X-axis | 0 | 0 | Equator at the Prime Meridian |
| Y-axis | 0 | 90 | Equator at 90-degrees East |
| Z-axis | 90 | 0 | North Pole |

See Also

`ecef2enu`

Introduced before R2006a

ecef2ned

Geocentric ECEF to local Cartesian NED

Syntax

```
[xNorth,yEast,zDown] = ecef2ned(X,Y,Z,lat0,lon0,h0,spheroid)  
[ ___ ] = ecef2ned( ___ ,angleUnit)
```

Description

[xNorth,yEast,zDown] = ecef2ned(X,Y,Z,lat0,lon0,h0,spheroid) returns coordinates in a local north-east-down (NED) Cartesian system corresponding to coordinates X, Y, Z in an Earth-Centered Earth-Fixed (ECEF) spheroid-centric Cartesian system. Any of the first six numeric input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

[___] = ecef2ned(___ ,angleUnit) adds angleUnit which specifies the units of inputs lat0, and lon0.

Input Arguments

X — ECEF x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the spheroid-centric ECEF system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the LengthUnit property of the spheroid object.

Data Types: single | double

Y — ECEF y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the spheroid-centric ECEF system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the spheroid object.

Data Types: `single` | `double`

Z — ECEF y-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid object.

lat0 — Geodetic latitude of local origin

scalar value | vector | matrix | N-D array

Geodetic latitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lat0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon0 — Longitude of local origin

scalar value | vector | matrix | N-D array

Longitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lon0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

h0 — Ellipsoidal height of local origin

scalar value | vector | matrix | N-D array

Ellipsoidal height of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `h0` is scalar, but it need not be. (It may refer to a moving platform, for example). Units are determined by the `LengthUnit` property of the spheroid input.

Data Types: `single` | `double`

spheroid — Reference spheroid

referenceEllipsoid | oblateSpheroid | referenceSphere

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. To create a spheroid object, use the creation function specific to the object, or the `wgs84Ellipsoid` function.

Example: `spheroid = referenceEllipsoid('GRS 80');`

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: `char` | `string`

Output Arguments

xNorth — Local NED x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the local NED system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid input.

yEast — Local NED y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the local NED system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid input.

zDown — Local NED z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the local NED system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid input.

See Also

ecef2aer | ecef2enu | geodetic2ned | ned2ecef

Introduced in R2012b

ecef2nedv

Rotate vector from geocentric ECEF to local NED

Syntax

```
[uNorth,vEast,wDown] = ecef2nedv(U,V,W,lat0,lon0)
[ ___ ] = ecef2nedv( ___ ,angleUnit)
```

Description

[uNorth,vEast,wDown] = ecef2nedv(U,V,W,lat0,lon0) returns Cartesian 3-vector components in a local north-east-down (NED) system corresponding to the 3-vector with components U, V, W in an Earth-Centered Earth-Fixed (ECEF) spheroid-centric Cartesian system. Any of the five numerical input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

[___] = ecef2nedv(___ ,angleUnit) adds angleUnit which specifies the units of inputs lat0 and lon0.

Input Arguments

U — Vector x-components in ECEF system

scalar value | vector | matrix | N-D array

x-components of one or more Cartesian vectors in the spheroid-centric ECEF system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: single | double

V — Vector y-components in ECEF system

scalar value | vector | matrix | N-D array

y-components of one or more Cartesian vectors in the spheroid-centric ECEF system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: single | double

W — Vector z-components in ECEF system

scalar value | vector | matrix | N-D array

z-components of one or more Cartesian vectors in the spheroid-centric ECEF system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: single | double

lat0 — Geodetic latitude of local origin

scalar value | vector | matrix | N-D array

Geodetic latitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lat0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: single | double

lon0 — Longitude of local origin

scalar value | vector | matrix | N-D array

Longitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lon0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: single | double

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: char | string

Output Arguments

uNorth — Vector x-components in NED system

scalar value | vector | matrix | N-D array

x-components of one or more Cartesian vectors in the local NED system, returned as a scalar value, vector, matrix, or N-D array.

vEast — Vector y-components in NED system

scalar value | vector | matrix | N-D array

y-components of one or more Cartesian vectors in the local NED system, returned as a scalar value, vector, matrix, or N-D array.

wDown — Vector z-components in NED system

scalar value | vector | matrix | N-D array

z-components of one or more Cartesian vectors in the local NED system, returned as a scalar value, vector, matrix, or N-D array.

See Also

[ecef2enuv](#) | [ecef2ned](#) | [ned2ecefv](#)

Introduced in R2012b

ecefOffset

Cartesian ECEF offset between geodetic positions

Syntax

```
[deltaX,deltaY,deltaZ] = ecefOffset(spheroid,lat1,lon1,h1,lat2,lon2,
h2)
[] = ecefOffset( ____,angleUnit)
```

Description

[deltaX,deltaY,deltaZ] = ecefOffset(spheroid,lat1,lon1,h1,lat2,lon2,h2) returns the offset from the geodetic position specified by lat1,lon1, and h1 to the position specified by lat2,lon2, and h2, as a Cartesian 3-vector with components deltaX,deltaY,deltaZ. The geodetic latitudes, longitudes, and heights refer to the reference body specified by the spheroid object, spheroid. The components deltaX,deltaY, and deltaZ refer to a spheroid-centric Earth-Centered Earth-Fixed (ECEF) Cartesian system. lat1,lon1, lat2, and lon2 are in degrees by default. h1 and h2 must be expressed in the same length unit as the spheroid. deltaX,deltaY, and deltaZ will be expressed in these units, also.

[] = ecefOffset(____,angleUnit) where angleUnit specifies the units of the latitude and longitude coordinates, either 'degrees' or 'radians'.

Examples

Calculate Cartesian ECEF Offset Between Geodetic Positions

Define two locations in geodetic coordinates. Note that heights are relative to the ellipsoid, not sea level. Thus, the height for Miami is a negative number.

```
latParis = dms2degrees([48 51 24]);
lonParis = dms2degrees([2 21 03]);
hParis = 80;
```

```
latMiami = dms2degrees([ 25 46 31]);  
lonMiami = dms2degrees([-80 12 32]);  
hMiami = -25;  
wgs84 = wgs84Ellipsoid('meters');
```

Calculate the offset vector between the two geodetic positions.

```
[dx,dy,dz] = ecefOffset(wgs84, ...  
    latParis,lonParis,hParis,latMiami,lonMiami,hMiami)
```

```
dx = -3.2236e+06
```

```
dy = -5.8359e+06
```

```
dz = -2.0235e+06
```

Calculate the straight-line (through the Earth) distance from Paris to Miami.

```
d = hypot(hypot(dx,dy),dz)
```

```
d = 6.9674e+06
```

Input Arguments

spheroid — Reference spheroid

referenceEllipsoid | oblateSpheroid | referenceSphere

Reference spheroid, specified as a referenceEllipsoid, oblateSpheroid, or referenceSphere object. To create a spheroid object, use the creation function specific to the object, or the wgs84Ellipsoid function.

Example: spheroid = referenceEllipsoid('GRS 80');

lat1 — Geodetic latitude in degrees

geodetic coordinate array

Geodetic latitude in degrees, specified as geodetic coordinate array.

Data Types: single | double

lon1 — Geodetic longitude in degrees

geodetic coordinate array

Geodetic longitude in degrees, specified as a geodetic coordinate array.

Data Types: single | double

h1 — Ellipsoidal height

numeric array

Ellipsoidal height, specified as numeric array

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64

lat2 — Geodetic latitude in degrees

geodetic coordinate array

Geodetic latitude in degrees, specified as geodetic coordinate array.

Data Types: single | double

lon2 — Geodetic longitude in degrees

geodetic coordinate array

Geodetic longitude in degrees, specified as a geodetic coordinate array.

Data Types: single | double

h2 — Ellipsoidal height

numeric array

Ellipsoidal height, specified as a numeric array.

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64

angleUnit — Units of the latitude and longitude coordinates

'degrees' | 'radians'

Units of the latitude and longitude coordinates, specified as 'degrees' or 'radians'.

Data Types: char

Output Arguments

deltaX — Offset between geodetic positions lat1 and lat2

geodetic coordinate array

Offset between geodetic positions lat1 and lat2, returned as a Cartesian 3-vector.

deltaY — Offset between geodetic positions lon1 and lon2

geodetic coordinate array

Offset between geodetic positions lon1 and lon2, returned as a Cartesian 3-vector.

deltaZ — Offset between geodetic positions h1 and h2

scalar

Offset between geodetic positions h1 and h2, returned as a Cartesian 3-vector.

See Also

[ecef2geodetic](#) | [geodetic2ecef](#) | [oblateSpheroid](#) | [referenceEllipsoid](#) | [referenceSphere](#)

Introduced in R2012b

egm96geoid

Read 15-minute gridded geoid heights from EGM96

Syntax

```
[Z, refvec] = egm96geoid(samplefactor)
[Z, refvec] = egm96geoid(samplefactor, latlim, lonlim)
```

Description

`[Z, refvec] = egm96geoid(samplefactor)` imports global geoid height in meters from the EGM96 geoid model. The data set is gridded at 15-minute intervals, but may be down-sampled as specified by the positive integer `samplefactor`. The result is returned in the regular data grid `Z` along with referencing vector `refvec`. At full resolution (a `samplefactor` of 1), `Z` will be 721-by-1441.

The gridded EGM96 data set must be on your path in a file named 'WW15MGH.GRD'.

`[Z, refvec] = egm96geoid(samplefactor, latlim, lonlim)` imports data for the part of the world within the specified latitude and longitude limits. The limits must be two-element vectors in units of degrees. Longitude limits can be defined in the range `[-180 180]` or `[0 360]`. For example, `lonlim = [170 190]` returns data centered on the dateline, while `lonlim = [-10 10]` returns data centered on the prime meridian.

Background

Although the Earth is round, it is not exactly a sphere. The shape of the Earth is usually defined by the geoid, which is defined as a gravitational equipotential surface, but can be conceptualized as the shape the ocean surface would take in the absence of waves, weather, and land. For cartographic purposes it is generally sufficient to treat the Earth as a sphere or ellipsoid of revolution. For other applications, a more detailed model of the geoid such as EGM 96 may be required. EGM 96 is a spherical harmonic model of the geoid complete to degree and order 360. This function reads from a file of gridded geoid heights derived from the EGM 96 harmonic coefficients.

Examples

Read the EGM 96 geoid grid for the world, taking every 10th point.

```
[N,refvec] = egm96geoid(10);
```

Read a subset of the geoid grid at full resolution and interpolate to find the geoid height at a point between grid points.

```
[N,refvec] = egm96geoid(1,[-10 -12],[129 132]);  
n = ltln2val(N,refvec,-11.1,130.22,'bicubic')
```

```
n =  
    52.7151
```

Tips

This function reads the 15-minute EGM96 grid file `WW15MGH.GRD`. The grid is available as either a DOS self-extracting compressed file or a UNIX compressed file. Do not modify the file once it has been extracted.

Note For details on locating map data for download over the Internet, see the following documentation at the MathWorks Web site: “Find Geospatial Data Online”.

Maps will extend a half a cell outside the requested map limits.

There are 721 rows and 1441 columns of values in the grid at full resolution. The low resolution data in `GEOID.MAT` is derived from the EGM 96 grid.

See Also

`ltln2val`

Introduced before R2006a

elevation

Local vertical elevation angle, range, and azimuth

Note `elevation` will be removed in a future release. Use `geodetic2aer` instead.

The reference point comes second in the `geodetic2aer` argument list, and the outputs are ordered differently. The replacement pattern is:

```
[azimuthangle, elevationangle, slanrange] = geodetic2aer(lat2,
lon2, alt2, lat1, lon1, alt1, spheroid, ...)
```

Unlike `elevation`, `geodetic2aer` requires a spheroid input, and it must be must be an `oblateSpheroid`, `referenceEllipsoid`, or `referenceSphere` object, not a 2-by-1 ellipsoid vector.

You can use the following steps to convert an ellipsoid vector, `ellipsoid`, to an `oblateSpheroid` object, `spheroid`:

- `spheroid = oblateSpheroid;`
- `spheroid.SemimajorAxis = ellipsoid(1);`
- `spheroid.Eccentricity = ellipsoid(2);`

When `elevation` is called with only 6 inputs, the GRS 80 reference ellipsoid, in meters, is used by default. To replace this usage, use `referenceEllipsoid('GRS80', 'meters')` as the spheroid input for `geodetic2aer`.

If an `angleunits` input is included, it must follow the spheroid input in the call to `geodetic2aer`, rather than preceding it.

You can specify the `lengthunits` parameter when calling `elevation`, but `geodetic2aer` has no such input. Instead, set the `LengthUnit` property of the input spheroid to the desired value. In this case a `referenceEllipsoid` or `referenceSphere` object must be used (not an `oblateSpheroid` object).

Syntax

```
[elevationangle, slanrange, azimuthangle] = ...
```

```
elevation(lat1,lon1,alt1,lat2,lon2,alt2)
[...] = elevation(lat1,lon1,alt1,lat2,lon2,alt2,...
    angleunits)
[...] = elevation(lat1,lon1,alt1,lat2,lon2,alt2,...
    angleunits,distanceunits)
[...] = elevation(lat1,lon1,alt1,lat2,lon2,alt2,...
    angleunits,ellipsoid)
```

Description

```
[elevationangle,slanrange,azimuthangle] = ...
```

`elevation(lat1,lon1,alt1,lat2,lon2,alt2)` computes the elevation angle, slant range, and azimuth angle of point 2 (with geodetic coordinates `lat2`, `lon2`, and `alt2`) as viewed from point 1 (with geodetic coordinates `lat1`, `lon1`, and `alt1`). The coordinates `alt1` and `alt2` are ellipsoidal heights. The elevation angle is the angle of the line of sight above the local horizontal at point 1. The slant range is the three-dimensional Cartesian distance between point 1 and point 2. The azimuth is the angle from north to the projection of the line of sight on the local horizontal. Angles are in units of degrees; altitudes and distances are in meters. The figure of the earth is the default ellipsoid (GRS 80).

Inputs can be vectors of points, or arrays of any shape, but must match in size, with the following exception: Elevation, range, and azimuth from a single point to a set of points can be computed very efficiently by providing scalar coordinate inputs for point 1 and vectors or arrays for point 2.

```
[...] = elevation(lat1,lon1,alt1,lat2,lon2,alt2,...
    angleunits) where angleunits specifies the units of the input and output angles. If
you omit angleunits, 'degrees' is assumed.
```

```
[...] = elevation(lat1,lon1,alt1,lat2,lon2,alt2,...
    angleunits,distanceunits) where distanceunits specifies the altitude and
slant-range units. If you omit distanceunits, 'meters' is the default. Any units value
recognized by unitsratio may be used.
```

```
[...] = elevation(lat1,lon1,alt1,lat2,lon2,alt2,...
    angleunits,ellipsoid) uses ellipsoid to specify the ellipsoid. ellipsoid is a
referenceSphere, referenceEllipsoid, or oblateSpheroid object, or a vector of
the form [semimajor_axis eccentricity]. If ellipsoid is supplied, the altitudes
must be in the same units as the semimajor axis, and the slant range will be returned in
```

these units. If `ellipsoid` is omitted, the default is a unit sphere. Distances are in meters unless otherwise specified.

Note The line-of-sight azimuth angles returned by `elevation` will generally differ slightly from the corresponding outputs of `azimuth` and `distance`, except for great circle azimuths on a spherical earth.

Examples


Find the elevation angle of a point 90 degrees from an observer assuming that the observer and the target are both 1000 km above the Earth.

```
lat1 = 0; lon1 = 0; alt1 = 1000*1000;
lat2 = 0; lon2 = 90; alt2 = 1000*1000;
elevang = elevation(lat1,lon1,alt1,lat2,lon2,alt2)
```

```
elevang =
    -45
```

Visually check the result using the `los2` line of sight function. Construct a data grid of zeros to represent the Earth's surface. The `los2` function with no output arguments creates a figure displaying the geometry.

```
Z = zeros(180,360);
refvec = [1 90 -180];
los2(Z,refvec,lat1,lon1,lat2,lon2,alt1,alt1);
```



See Also

geodetic2aer

Introduced before R2006a

ellipse1

Geographic ellipse from center, semimajor axes, eccentricity, and azimuth

Syntax

```
[lat,lon] = ellipse1(lat0,lon0,ellipse)
[lat,lon] = ellipse1(lat0,lon0,ellipse,offset)
[lat,lon] = ellipse1(lat0,lon0,ellipse,offset,az)
[lat,lon] = ellipse1(lat0,lon0,ellipse,offset,az,ellipsoid)
[lat,lon] = ellipse1( __ ,angleUnit)
[lat,lon] =
ellipse1(lat0,lon0,ellipse,offset,az,ellipsoid,angleUnit,npts)
[lat,lon] = ellipse1(trackStr,...)
mat = ellipse1(...)
```

Description

`[lat,lon] = ellipse1(lat0,lon0,ellipse)` computes ellipse(s) with center(s) at `lat0,lon0`. The ellipse is defined by the third input, which is of the form `[semimajor axis, eccentricity]`, where the eccentricity input can be a two-element row vector or a two-column matrix. The ellipse input must have the same number of rows as the input scalar or column vectors `lat0` and `lon0`. The input semimajor axis is in degrees of arc length on a sphere. All ellipses are oriented so that their major axes run north-south.

`[lat,lon] = ellipse1(lat0,lon0,ellipse,offset)` computes the ellipse(s) where the major axis is rotated from due north by an azimuth offset. The `offset` angle is measured clockwise from due north. If `offset = []`, then no offset is assumed.

`[lat,lon] = ellipse1(lat0,lon0,ellipse,offset,az)` uses the input `az` to define the ellipse arcs computed. The arc azimuths are measured clockwise from due north. If `az` is a column vector, then the arc length is computed from due north. If `az` is a two-column matrix, then the ellipse arcs are computed starting at the azimuth in the first column and ending at the azimuth in the second column. If `az = []`, then a complete ellipse is computed.

`[lat,lon] = ellipse1(lat0,lon0,ellipse,offset,az,ellipsoid)` computes the ellipse on the ellipsoid defined by the input `ellipsoid`. `ellipsoid` is a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. If omitted, the unit sphere, is assumed. When an ellipsoid is supplied, the input semimajor axis must be in the same units as the ellipsoid semimajor axes. In this calling form, the units of the ellipse semimajor axis are not assumed to be in degrees.

`[lat,lon] = ellipse1(____,angleUnit)` where `angleUnit` defines the units of the inputs and outputs. `angleUnit` can be `'degrees'` or `'radians'`. If you omit `angleUnit`, `ellipse1` uses `'degrees'`.

`[lat,lon] = ellipse1(lat0,lon0,ellipse,offset,az,ellipsoid,angleUnit,npts)` uses the scalar `npts` to determine the number of points per ellipse computed. If `npts` is omitted, 100 points are used.

`[lat,lon] = ellipse1(trackStr,...)` where `trackStr` specifies either great circle (`'gc'`) or rhumb line (`'rh'`) distances from the ellipse center.

`mat = ellipse1(...)` returns a single output argument where `mat = [lat lon]`. This is useful if only one ellipse is computed.

You can define multiple ellipses with a common center by providing scalar `lat0` and `lon0` inputs and a two-column ellipse matrix.

Examples

Create and plot the small ellipse centered at $(0^{\circ},0^{\circ})$, with a semimajor axis of 10° and a semiminor axis of 5° .


```
axesm mercator
ecc = axes2ecc(10,5);
plotm(0,0,'r+')
[elat,elon] = ellipse1(0,0,[10 ecc],45);
plotm(elat,elon)
```

If the desired radius is known in some nonangular distance unit, use the radius returned by the `earthRadius` function as the ellipsoid input to set the range units. (Use an empty azimuth entry to specify a full ellipse.)

```
[elat,elon] = ellipse1(0,0,[550 ecc],45,[],earthRadius('nm'));  
plotm(elat,elon,'m--')
```

For just an arc of the ellipse, enter an azimuth range:

```
[elat,elon] = ellipse1(0,0,[5 ecc],45,[-30 70]);  
plotm(elat,elon,'c-')
```



See Also

[axes2ecc](#) | [scircle1](#) | [track1](#)

Introduced before R2006a

encodem

Fill in regular data grid from seed values and locations

Syntax

```
newgrid = encodem(Z,seedmat)
newgrid = encodem(Z,seedmat,stopvals)
```

Description

`newgrid = encodem(Z,seedmat)` fills in regions of the input data grid, `Z`, with desired new values. The boundary consists of the edges of the matrix and any entries with the value 1. The *seeds*, or starting points, and the values associated with them, are specified by the three-column matrix `seedmat`, the rows of which have the form [row column value].

`newgrid = encodem(Z,seedmat,stopvals)` allows you to specify a vector, `stopvals`, of stopping values. Any value that is an element of `stopvals` will act as a boundary.

This function *fills in* regions of data grids with desired values. If a *boundary* exists, the new value replaces all entries in all four directions until the boundary is reached. The boundary is made up of selected stopping values and the edges of the matrix. The new value tries to flood the region exhaustively, stopping only when no new spaces can be reached by moving up, down, left, or right without hitting a stopping value.

Examples

For this imaginary map, fill in the upper right region with 7s and the lower left region with 3s:

```
Z = eye(4)
```

```
Z =
     1     0     0     0
     0     1     0     0
     0     0     1     0
     0     0     0     1
```

```
0    1    0    0
0    0    1    0
0    0    0    1
```

```
newgrid = encodem(Z,[4,1,3; 1,4,7])
```

```
newgrid =
 1    7    7    7
 3    1    7    7
 3    3    1    7
 3    3    3    1
```

See Also

getseeds | imbedm

Introduced before R2006a

enu2aer

Local Cartesian ENU to local spherical AER

Syntax

```
[az,elev,slantRange] = enu2aer(xEast,yNorth,zUp)
[ ___ ] = enu2aer( ___ ,angleUnit)
```

Description

[az,elev,slantRange] = enu2aer(xEast,yNorth,zUp) returns coordinates in a local spherical system corresponding to coordinates xEast, yNorth, zUp in a local east-north-up (ENU) Cartesian system having the same local origin. Any of the three numerical input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

[___] = enu2aer(___ ,angleUnit) adds angleUnit which specifies the units outputs az, elev.

Input Arguments

xEast — Local ENU x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the local ENU system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: single | double

yNorth — Local ENU y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the local ENU system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: single | double

zUp — Local ENU z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the local ENU system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: single | double

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: char | string

Output Arguments

az — Azimuth angles

scalar value | vector | matrix | N-D array

Azimuth angles in the local spherical system, returned as a scalar value, vector, matrix, or N-D array. Azimuths are measured clockwise from north. Units are determined by the input argument `angleUnit`, if supplied; values are in degrees, otherwise. When in degrees, they lie in the half-open interval [0 360).

elev — Elevation angles

scalar value | vector | matrix | N-D array

Elevation angles in the local spherical system, returned as a scalar value, vector, matrix, or N-D array. Elevations are with respect to a plane perpendicular to the spheroid surface normal. Units determined by the input argument `angleUnit`, if supplied; values are in degrees, otherwise. When in degrees, they lie in the closed interval [-90 90].

slantRange — Distances from local origin

scalar value | vector | matrix | N-D array

Distances from origin in the local spherical system, returned as a scalar, vector, matrix, or N-D array. The straight-line, 3-D Cartesian distance is computed.

See Also

aer2enu | ned2aer

Introduced in R2012b

enu2ecef

Local Cartesian ENU to geocentric ECEF

Syntax

```
[X,Y,Z] = enu2ecef(xEast,yNorth,zUp,lat0,lon0,h0,spheroid)  
[ ___ ] = enu2ecef( ___,angleUnit)
```

Description

`[X,Y,Z] = enu2ecef(xEast,yNorth,zUp,lat0,lon0,h0,spheroid)` returns Earth-Centered Earth-Fixed (ECEF) spheroid-centric Cartesian coordinates corresponding to coordinates `xEast`, `yNorth`, `zUp` in a local east-north-up (ENU) Cartesian system. Any of the first six numeric input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

`[___] = enu2ecef(___,angleUnit)` adds `angleUnit` which specifies the units of inputs `lat0` and `lon0`.

Input Arguments

xEast — Local ENU x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the local ENU system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the `spheroid` input.

Data Types: `single` | `double`

yNorth — Local ENU y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the local ENU system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the `spheroid` input.

Data Types: `single` | `double`

zUp — Local ENU z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the local ENU system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the `spheroid` input.

Data Types: `single` | `double`

lat0 — Geodetic latitude of local origin

scalar value | vector | matrix | N-D array

Geodetic latitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lat0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon0 — Longitude of local origin

scalar value | vector | matrix | N-D array

Longitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lon0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

h0 — Ellipsoidal height of local origin

scalar value | vector | matrix | N-D array

Ellipsoidal height of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `h0` is scalar, but it need not be. (It may refer to a moving platform, for example). Units are determined by the `LengthUnit` property of the `spheroid` input.

Data Types: `single` | `double`

spheroid — Reference spheroid

`referenceEllipsoid` | `oblateSpheroid` | `referenceSphere`

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. To create a spheroid object, use the creation function specific to the object, or the `wgs84Ellipsoid` function.

Example: `spheroid = referenceEllipsoid('GRS 80');`

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: `char` | `string`

Output Arguments

X — ECEF x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the `spheroid` object.

Y — ECEF y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the `spheroid` object.

Z — ECEF z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the `spheroid` object.

See Also

aer2ecef | ecef2enu | enu2geodetic | ned2ecef

Introduced in R2012b

enu2ecefv

Rotate vector from local ENU to geocentric ECEF

Syntax

```
[U,V,W] = enu2ecefv(uEast,vNorth,wUp,lat0,lon0)
[ ___ ] = enu2ecefv( ___ ,angleUnit)
```

Description

[U,V,W] = enu2ecefv(uEast,vNorth,wUp,lat0,lon0) returns coordinates in a local spherical system corresponding to coordinates uEast, vNorth, and wUp, in a local north-east-up (ENU) Cartesian system having the same local origin. Any of the three numerical input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

[___] = enu2ecefv(___ ,angleUnit) adds angleUnit which specifies the units of inputs lat0 and lon0.

Input Arguments

uEast — Vector x-components in ENU system

scalar value | vector | matrix | N-D array

x-components of one or more Cartesian vectors in the local ENU system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: single | double

vNorth — Vector y-components in ENU system

scalar value | vector | matrix | N-D array

y-components of one or more Cartesian vectors in the local ENU system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: single | double

wUp — Vector z-components in ENU system

scalar value | vector | matrix | N-D array

z-components of one or more Cartesian vectors in the local ENU system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: `single` | `double`

lat0 — Geodetic latitude of local origin

scalar value | vector | matrix | N-D array

Geodetic latitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lat0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon0 — Longitude of local origin

scalar value | vector | matrix | N-D array

Longitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lon0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: `char` | `string`

Output Arguments

U — Vector x-components in ECEF system

scalar value | vector | matrix | N-D array

x-components of one or more Cartesian vectors in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array.

V – Vector y-components in ECEF system

scalar value | vector | matrix | N-D array

y-components of one or more Cartesian vectors in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array.

W – Vector z-components in ECEF system

scalar value | vector | matrix | N-D array

z-components of one or more Cartesian vectors in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array.

See Also

ecef2enu | enu2ecef | ned2ecefv

Introduced in R2012b

enu2geodetic

Local Cartesian ENU to geodetic

Syntax

```
[lat,lon,h] = enu2geodetic(xEast,yNorth,zUp,lat0,lon0,h0,spheroid)  
[ ___ ] = enu2geodetic( ___,angleUnit)
```

Description

`[lat,lon,h] = enu2geodetic(xEast,yNorth,zUp,lat0,lon0,h0,spheroid)` returns geodetic coordinates corresponding to coordinates `xEast`, `yNorth`, `zUp` in a local east-north-up (ENU) Cartesian system. Any of the first six numeric input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

`[___] = enu2geodetic(___,angleUnit)` adds `angleUnit` which specifies the units of inputs `lat0`, `lon0`, and outputs `lat`, `lon`.

Input Arguments

xEast — Local ENU x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the local ENU system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the `spheroid` input.

Data Types: `single` | `double`

yNorth — Local ENU y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the local ENU system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the `spheroid` input.

Data Types: `single` | `double`

zUp — Local ENU z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the local ENU system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the `spheroid` input.

Data Types: `single` | `double`

lat0 — Geodetic latitude of local origin

scalar value | vector | matrix | N-D array

Geodetic latitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lat0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon0 — Longitude of local origin

scalar value | vector | matrix | N-D array

Longitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lon0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

h0 — Ellipsoidal height of local origin

scalar value | vector | matrix | N-D array

Ellipsoidal height of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `h0` is scalar, but it need not be. (It may refer to a moving platform, for example). Units are determined by the `LengthUnit` property of the `spheroid` input.

Data Types: `single` | `double`

spheroid — Reference spheroid

`referenceEllipsoid` | `oblateSpheroid` | `referenceSphere`

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. To create a spheroid object, use the creation function specific to the object, or the `wgs84Ellipsoid` function.

Example: `spheroid = referenceEllipsoid('GRS 80');`

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: `char` | `string`

Output Arguments

lat — Geodetic latitudes

scalar value | vector | matrix | N-D array

Geodetic latitudes of one or more points, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the input argument `angleUnit`, if supplied; values are in degrees, otherwise. When in degrees, they lie in the closed interval [-90 90].

lon — Longitudes

scalar value | vector | matrix | N-D array

Longitudes of one or more points, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the input argument `angleUnit`, if supplied; values are in degrees, otherwise. When in degrees, they lie in the interval [-180 180].

h — Ellipsoidal heights

scalar value | vector | matrix | N-D array

Ellipsoidal heights of one or more points, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the `spheroid` object

See Also

aer2geodetic | enu2ecef | geodetic2enu | ned2geodetic

Introduced in R2012b

epsm

Accuracy in angle units for certain map computations

Note epsm will be removed in a future release. If necessary, you can replace the expressions listed in the following table with the constants shown:

| | |
|-------------|-----------------|
| epsm() | 1.0E-6 |
| epsm('deg') | 1.0E-6 |
| epsm('rad') | deg2rad(1.0E-6) |

Syntax

```
epsm  
epsm(units)
```

Description

epsm is the limit of map angular precision. It is useful in avoiding trigonometric singularities, among other things.

epsm(units) returns the same angle in units corresponding to any valid angle units character vector. The default is 'degrees'.

Examples

The value of epsm is 10^{-6} degrees. To put this in perspective, in terms of an angular arc length, the distance is

```
epsmkm = deg2km(epsm)
```

```
epsmkm =  
    1.1119e-04      % kilometers
```

This is about 11 centimeters, a very small distance on a global scale.

See Also

roundn

Introduced before R2006a

eqa2grn

Convert from equal area to Greenwich coordinates

Syntax

```
[lat,lon] = eqa2grn(x,y)
[lat,lon] = eqa2grn(x,y,origin)
[lat,lon] = eqa2grn(x,y,origin,ellipsoid)
[lat,lon] = eqa2grn(x,y,origin,units)
mat = eqa2grn(x,y,origin...)
```

Description

`[lat,lon] = eqa2grn(x,y)` converts the equal-area coordinate points `x` and `y` to the Greenwich (standard geographic) coordinates `lat` and `lon`.

`[lat,lon] = eqa2grn(x,y,origin)` specifies the location in the Greenwich system of the `x-y` origin (0,0). The two-element vector `origin` must be of the form `[latitude longitude]`. The default places the origin at the Greenwich coordinates (0°₀°).

`[lat,lon] = eqa2grn(x,y,origin,ellipsoid)` specifies the ellipsoidal model of the figure of the Earth using `ellipsoid`. `ellipsoid` is a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. The ellipsoid is a unit sphere by default.

`[lat,lon] = eqa2grn(x,y,origin,units)` specifies the units for the outputs, where `units` is any valid angle units value. The default value is `'degrees'`.

`mat = eqa2grn(x,y,origin...)` packs the outputs into a single variable.

This function converts data from equal-area `x-y` coordinates to geographic (latitude-longitude) coordinates. The opposite conversion can be performed with `grn2eqa`.

Examples

```
[lat,lon] = eqa2grn(.5,.5)
```

```
lat =  
 30.0000  
lon =  
 28.6479
```

See Also

grn2eqa | hista

Introduced before R2006a

etopo

Read gridded global relief data (ETOPO products)

Syntax

```
[Z, refvec] = etopo
[Z, refvec] = etopo(samplefactor)
[Z, refvec] = etopo(samplefactor, latlim, lonlim)
[Z, refvec] = etopo(folder, ...)
[Z, refvec] = etopo(filename, ...)
[Z, refvec] = etopo({'etopo5.northern.bat',
'etopo5.southern.bat'}, ...)
```

Description

[Z, refvec] = `etopo` reads the ETOPO data for the entire world from the ETOPO data in the current folder. The `etopo` function searches the current folder first for ETOPO1c binary data, then ETOPO2V2c binary data, then ETOPO2 (2001) binary data, then ETOPO5 binary data, and finally ETOPO5 ASCII data. Once the function finds a case-insensitive file name match, it reads the data. See the table Supported ETOPO Data File Names for a list of possible file names. The `etopo` function returns the data grid, Z, as an array of elevations. Data values, in whole meters, represent the elevation of the center of each cell. `refvec`, the associated three-element referencing vector, geolocates Z.

[Z, refvec] = `etopo(samplefactor)` reads the data for the entire world, downsampling the data by `samplefactor`. The scalar integer `samplefactor` when equal to 1 gives the data at its full resolution (10800 by 21600 values for ETOPO1 data, 5400 by 10800 values for ETOPO2 data, and 2160 by 4320 values for ETOPO5 data). When `samplefactor` is an integer n greater than one, the `etopo` function returns every n^{th} point. If you omit `samplefactor` or leave it empty, it defaults to 1. (If the `etopo` function reads an older, ASCII ETOPO5 data set, then `samplefactor` must divide evenly into the number of rows and columns of the data file.)

[Z, refvec] = `etopo(samplefactor, latlim, lonlim)` reads the data for the part of the world within the specified latitude and longitude limits. Specify the limits of

the desired data as two-element vectors of latitude, `latlim`, and longitude, `lonlim`, in degrees. Specify the elements of `latlim` and `lonlim` in ascending order. Specify `lonlim` in the range `[0 360]` for ETOPO5 data and `[-180 180]` for ETOPO2 and ETOPO1 data. If `latlim` is empty, the latitude limits are `[-90 90]`. If `lonlim` is empty, the file type determines the longitude limits.

`[Z, refvec] = etopo(folder, ...)` allows you to use the variable `folder` to specify the path for the ETOPO data file. Otherwise, the `etopo` function searches the current folder for the data.


`[Z, refvec] = etopo(filename, ...)` reads the ETOPO data from the file specified by the case-insensitive string scalar or character vector `filename`. The name of the ETOPO file is as referenced in the ETOPO data file names table. Include the folder name in `filename` or place the file in the current folder or in a folder on the MATLAB path.

`[Z, refvec] = etopo({'etopo5.northern.bat', 'etopo5.southern.bat'}, ...)` reads the ETOPO data from the specified case-insensitive ETOPO5 ASCII data files. Place the files in the current folder or in a folder on the MATLAB path.

Examples


Read and display ETOPO2V2c data from the file `'ETOP02V2c_i2_LSB.bin'` downsampled to half-degree cell size and display the boundary of the land areas.

```
samplefactor = 15;
[Z, refvec] = etopo('ETOP02V2c_i2_LSB.bin', samplefactor);
figure
worldmap world
geoshow(Z, refvec, 'DisplayType', 'texturemap');
demcmap(Z, 256);
geoshow('landareas.shp', 'FaceColor', 'none', ...
        'EdgeColor', 'black');
```



Read and display ETOPO1 data for a region around Australia.

```
figure
worldmap australia
mstruct = gcm;
latlim = mstruct.maplatlimit;
lonlim = mstruct.maplonlimit;
[Z, refvec] = etopo('etopo1_ice_c.flt', 1, latlim, lonlim);
geoshow(Z, refvec, 'DisplayType', 'surface');
demcmap(Z, 256);
```



Definitions

ETOPO Models

According to the National Geophysical Data Center (NGDC) Web site, ETOPO models combine regional and global land topography and ocean bathymetry data from many data sources. ETOPO1, the most recent model, has an Ice Surface version showing the top of the Antarctic and Greenland ice sheets and a Bedrock version showing the bedrock below the ice sheets. For detailed information about the data sources used to create the ETOPO1 model, see the NGDC Web site. NGDC lists the ETOPO2 and ETOPO5 models as deprecated but still available.

| Model | Cell Size | Date Available |
|----------|--------------|----------------|
| ETOPO1 | 1-arc-minute | March 2009 |
| ETOPO2v2 | 2-minute | 2006 |
| ETOPO2 | 2-minute | 2001 |
| ETOPO5 | 5-minute | 1988 |

Tips

Supported ETOPO Data File Names

| Format | Filenames |
|------------------|---|
| ETOPO1c (cell) | <ul style="list-style-type: none">• etopo1_ice_c.flt• etopo1_bed_c.flt• etopo1_ice_c_f4.flt• etopo1_bed_c_f4.flt• etopo1_ice_c_i2.bin• etopo1_bed_c_i2.bin |
| ETOPO2V2c (cell) | <ul style="list-style-type: none">• ETOP02V2c_i2_MSB.bin• ETOP02V2c_i2_LSB.bin• ETOP02V2c_f4_MSB.flt• ETOP02V2c_f4_LSB.flt• ETOP02V2c.hdf |
| ETOPO2 (2001) | <ul style="list-style-type: none">• ETOP02.dos.bin• ETOP02.raw.bin |
| ETOPO5 (binary) | <ul style="list-style-type: none">• ETOP05.DOS• ETOP05.DAT |
| ETOPO5 (ASCII) | <ul style="list-style-type: none">• etopo5.northern.bat• etopo5.southern.bat |

- For details on locating ETOPO data for download over the Internet, see the following documentation at the MathWorks Web site: “Find Geospatial Data Online”.

References

- [1] “2-minute Gridded Global Relief Data (ETOPO2v2),” U.S. Department of Commerce, National Oceanic and Atmospheric Administration, National Geophysical Data Center, 2006.

- [2] Amante, C. and B. W. Eakins, "ETOPO1 1 Arc-Minute Global Relief Model: Procedures, Data Sources and Analysis," *NOAA Technical Memorandum NESDIS NGDC-24*, March 2009.
- [3] "Digital Relief of the Surface of the Earth," *Data Announcement 88-MGG-02*, NOAA, National Geophysical Data Center, Boulder, Colorado, 1988.
- [4] "ETOPO2v2 Global Gridded 2-minute Database," National Geophysical Data Center, National Oceanic and Atmospheric Administration, U.S. Dept. of Commerce.

See Also

gtopo30 | tbase | usgsdem

Introduced before R2006a

etopo5

Read global 5-min digital terrain data

Syntax

Note etopo5 will be removed in a future version; use etopo instead.

```
[Z, refvec] = etopo5
[Z, refvec] = etopo5(samplefactor)
[[Z, refvec] = etopo5(samplefactor, latlim, lonlim)
[Z, refvec] = etopo5(folder, ...)
[Z, refvec] = etopo5(file, ...)
```

Description

[Z, refvec] = etopo5 reads the topography data for the entire world for the data in the current folder. The current folder is searched first for ETOPO2 binary data, followed by ETOPO5 binary data, followed by ETOPO5 ASCII data from the file names etopo5.northern.bat and etopo5.southern.bat. Once a match is found the data is read. The data grid, Z, is returned as an array of elevations. Data values are in whole meters, representing the elevation of the center of each cell. refvec is the associated three-element referencing vector that geolocates Z.

[Z, refvec] = etopo5(samplefactor) reads the data for the entire world, downsampling the data by samplefactor. samplefactor is a scalar integer, which when equal to 1 gives the data at its full resolution (1080 by 4320 values). When samplefactor is an integer n greater than one, every nth point is returned. samplefactor must divide evenly into the number of rows and columns of the data file. If samplefactor is omitted or empty, it defaults to 1.

[[Z, refvec] = etopo5(samplefactor, latlim, lonlim) reads the data for the part of the world within the specified latitude and longitude limits. The limits of the desired data are specified as two-element vectors of latitude, latlim, and longitude, lonlim, in degrees. The elements of latlim and lonlim must be in ascending order. If

latlim is empty the latitude limits are [-90 90]. lonlim must be specified in the range [0 360]. If lonlim is empty, the longitude limits are [0 360].

[Z, refvec] = etopo5(folder, ...) allows the path for the data file to be specified by folder rather than the current folder.

[Z, refvec] = etopo5(file, ...) reads the data from file, where file is a character vector or a cell array of character vectors containing the name or names of the data files.

ETOPO5 is being superseded by ETOPO2 and the TerrainBase digital terrain model. See the tbase external interface function for more information.

Note For details on locating map data for download over the Internet, see the following documentation at the MathWorks Web Site: “Find Geospatial Data Online”.

Examples

Example 1

Read every tenth point in the data set:

```
% Read and display the ETOPO5 data from the folder 'etopo5'
% downsampled by a factor of 10.
[Z, refvec] = etopo5('etopo5',10);
axesm merc
geoshow(Z, refvec, 'DisplayType', 'surface');
demcmap(Z);
```

Example 2

Read in data for Korea and Japan at the full resolution:

```
samplefactor = 1; latlim = [30 45]; lonlim = [115 145];
[Z, refvec] = etopo5(samplefactor, latlim, lonlim);
whos Z
```

| Name | Size | Bytes | Class |
|------|---------|--------|--------------|
| Z | 180x360 | 518400 | double array |

See Also

etopo | gtopo30 | tbase | usgsdem

Introduced before R2006a

extractfield

Field values from structure array

Syntax

```
a = extractfield(S,name)
```

Description

`a = extractfield(S,name)` returns the field values specified by the field name of structure `S`.

Examples

Extract Fields From Structure


Load a structure that contains information about roads in Concord, MA.

```
roads = shaperead('concord_roads.shp');  
r = roads(1:5)
```

```
r = 5x1 struct array with fields:  
    Geometry  
    BoundingBox  
    X  
    Y  
    STREETNAME  
    RT_NUMBER  
    CLASS  
    ADMIN_TYPE  
    LENGTH
```

Get the x - and y -coordinates of the roads. Display the map, and highlight the first few elements using the color magenta.

```
hold on
plot(extractfield(roads,'X'),extractfield(roads,'Y'));
plot(extractfield(r,'X'),extractfield(r,'Y'),'m');
```



Extract the names of the roads, stored in the field `STREETNAME`. The field values are character vectors, so the result is returned in a cell array.

```
names = extractfield(r,'STREETNAME')
```

```
names = 1x5 cell array
Columns 1 through 4
```

```
{0x0 char}    {'WRIGHT FARM'}    {'WRIGHT FARM'}    {'WRIGHT FARM'}
```

```
Column 5
{'WRIGHT FARM'}
```

Extract the X field from the structure and examine the format of the returned values. All values have the same numeric data type (`double`), so the result is returned in a vector.

```
uniformType = extractfield(r, 'X')
```

```
uniformType = 1x42
105 ×
```

```
2.0884    2.0884    2.0884    2.0883    2.0883    2.0882    2.0882    2.0882    2.0882
```

For illustrative purposes, change the X field value in one of the elements to have a different data type. This command converts the second element to data type `single`.

```
r(2).X = single(r(2).X);
```

Extract the X field values again. This time, the values have different data types, so the result is returned in a cell array.

```
mixedType = extractfield(r, 'X')
```

```
mixedType = 1x5 cell array
Columns 1 through 4
```

```
{1x14 double}    {1x8 single}    {1x5 double}    {1x12 double}
```

```
Column 5
```

```
{1x3 double}
```

Input Arguments

S — Structure

structure

Structure, specified as a structure.

name — Field name

string scalar | character vector

Field name, specified as a case-sensitive string scalar or character vector.

Output Arguments

a — Extracted field values

1-by-*n* numeric vector | 1-by-*n* cell array

Extracted field values, returned as a 1-by-*n* numeric vector or cell array. *n* is the total number of elements in the field name of structure *S*, that is, $n = \text{ numel}([S(:).(\text{name})])$. *a* is a cell array if any field values in the field name contain a character vector or if the field values are not uniform in type; otherwise *a* is the same type as the field values. The shape of the input field is not preserved in *a*.

See Also

shaperead | struct

Introduced before R2006a

extractm

Coordinate data from line or patch display structure

Note `extractm` will be removed in a future release. The use of display structures is not recommended. Use `geoshape` vectors instead.

Syntax

```
[lat,lon] = extractm(display_struct,object_str)
[lat,lon] = extractm(display_struct,object_strings)
[lat,lon] = extractm(display_struct,object_strings,searchmethod)
[lat,lon] = extractm(display_struct)
[lat,lon,indx] = extractm(...)
mat = extractm(...)
```

Description

`[lat,lon] = extractm(display_struct,object_str)` extracts latitude and longitude coordinates from those elements of `display_struct` having 'tag' fields that begin with the string scalar or character vector specified by `object_str`. `display_struct` is a Mapping Toolbox display structure in which the 'type' field has a value of either 'line' or 'patch'. The output `lat` and `lon` vectors include NaNs to separate the individual map features. The comparison of 'tag' values is not case-sensitive.

`[lat,lon] = extractm(display_struct,object_strings)` selects features with 'tag' fields matching any of several different string scalar or character vectors. `object_strings` is a string scalar, character vector, cell array of character vectors, or character array. `extractm` strips trailing spaces from features listed in character arrays before matching.

`[lat,lon] = extractm(display_struct,object_strings,searchmethod)` specifies the method used to match the values of the 'tag' field in `display_struct`. `searchmethod` can be one of these values:

| | |
|------------|---|
| 'strmatch' | Search for matches at the beginning of the tag |
| 'findstr' | Search within the tag |
| 'exact' | Search for exact matches. Note that when <i>searchmethod</i> is specified the search is case-sensitive. |

[lat,lon] = extractm(display_struct) extracts all vector data from the input map structure.


[lat,lon,indx] = extractm(...) also returns the vector *indx* identifying which elements of *display_struct* met the selection criteria.

mat = extractm(...) returns the vector data in a single matrix, where *mat* = [lat
lon].

Examples

Extract the District of Columbia from the low-resolution U.S. vector data:

```
load greatlakes
[lat, lon] = extractm(greatlakes, 'Erie');
axesm mercator
geoshow(lat,lon, 'DisplayType','polygon', 'FaceColor','blue')
```



Tips

A Version 1 display structure is a MATLAB structure that can contain line, patch, text, regular data grid, geolocated data grid, and certain other objects and fixed attributes. In

Mapping Toolbox Version 2, a new data structure for vector geodata was introduced (called a mapstruct or a geostruct, depending on whether coordinates it contains are projected or unprojected). Geostructs and mapstructs have few required fields and can include any number of user-defined fields, giving them much greater flexibility to represent vector geodata. For information about the contents and format of display structures, see “Version 1 Display Structures” on page 1-257 in the reference page for `display`. For information about converting display structures to geographic data structures, see the reference page for `updategeostruct`, which performs such conversions.

See Also

Functions

`display` | `extractfield` | `geoshow` | `mapshow` | `mlayers` | `updategeostruct`

Objects

`geoshape`

Introduced before R2006a

fieldnames

Return dynamic property names of geographic or planar vector

Syntax

```
names = fieldnames(v)
```

Description

`names = fieldnames(v)` returns the names of the dynamic properties of geographic or planar vector `v`.

Examples

View Dynamic Properties of a Mapshape Vector

Create a mapshape vector.

```
ms = mapshape(shaperead('tsunamis'));
```

Display all dynamic properties of the mapshape vector. The displayed properties exclude the Collection properties `Geometry` and `Metadata` and the required mapshape Vertex properties `X` and `Y`.

```
fieldnames(ms)
```

```
ans = 18x1 cell array
    {'Year'      }
    {'Month'     }
    {'Day'       }
    {'Hour'      }
    {'Minute'    }
    {'Second'    }
    {'Val_Code'  }
    {'Validity'  }
```



```
{ 'Cause_Code' }  
{ 'Cause' }  
{ 'Eq_Mag' }  
{ 'Country' }  
{ 'Location' }  
{ 'Max_Height' }  
{ 'Iida_Mag' }  
{ 'Intensity' }  
{ 'Num_Deaths' }  
{ 'Desc_Deaths' }
```

Input Arguments

v — Geographic or planar vector

geopoint, geoshape, mappoint, or mapshape object

Geographic or planar vector, specified as a `geopoint`, `geoshape`, `mappoint`, or `mapshape` object.

Output Arguments

names — Names of dynamic properties

cell array

Names of dynamic properties of vector `v`, returned as a cell array.

See Also

`disp` | `properties`

Introduced in R2012a

fill3m

Project filled 3-D patch objects on map axes

Syntax

```
h = fill3m(lat,lon,z,cdata)
h = fill3m(lat,lon,z,PropertyName,PropertyValue,...)
```


Description

`h = fill3m(lat,lon,z,cdata)` projects and displays any patch object with vertices defined by vectors `lat` and `lon` to the current map axes. The scalar `z` indicates the altitude plane at which the patch is displayed. The input `cdata` defines the patch face color. The patch handle or handles, `h`, can be returned.

`h = fill3m(lat,lon,z,PropertyName,PropertyValue,...)` allows any property name/property value pair supported by `patch` to be assigned to the `fill3m` object.

Examples

```
lat = [30 15 0 0 0 15 30 30]';
lon = [-60 -60 -60 0 60 60 60 0]';
axesm bonne; framem
view(3)
fill3m(lat,lon,2,'b')
```



See Also

`fillm` | `patchesm` | `patchm`

Introduced before R2006a

fillm

Project filled 2-D patch objects on map axes

Syntax

```
h = fillm(lat,lon,cdata)
h = fillm(lat,lon,'PropertyName',PropertyValue,...)
```


Description

`h = fillm(lat,lon,cdata)` projects and displays any patch object with vertices defined by the vectors `lat` and `lon` to the current map axes. The input `cdata` defines the patch face color. The patch handle or handles, `h`, can be returned.

`h = fillm(lat,lon,'PropertyName',PropertyValue,...)` allows any property name/property value pair supported by patch to be assigned to the `fillm` object.

Examples

```
lat = [30 15 0 0 0 15 30 30]';
lon = [-60 -60 -60 0 60 60 60 0]';
axesm bonne; framem
fillm(lat,lon,'b')
```



See Also

[fill3m](#) | [patchesm](#) | [patchm](#)

Introduced before R2006a

filterm

Filter latitudes and longitudes based on underlying data grid

Syntax

```
[latout,lonout] = filterm(lat,lon,Z,R,allowed)
[latout,lonout,indx] = filterm( ___ )
```

Description

`[latout,lonout] = filterm(lat,lon,Z,R,allowed)` filters a set of latitudes and longitudes to include only those data points which have a corresponding value in Z equal to allowed. R can be a geographic raster reference object, a referencing vector, or a referencing matrix.

`[latout,lonout,indx] = filterm(___)` filters a set of latitudes and longitudes, returning indices of the included points in `indx`.

Examples

Filter topo Dataset

Load the topo dataset. This creates several variables in the workspace.

```
load topo
```

Select points along the equator with 5 deg spacing.


```
lon = (0:5:360)';
lat = zeros(size(lon));
```

Filter the points.

```
land = topo>0;
[newlat,newlon] = filterm(lat,lon,land,topolegend,1);
```


Map the terrain.

```
geoshow(topo,topolegend,'DisplayType','texturemap')
```




Show all the points in red.

```
geoshow(lat,lon,'DisplayType','point','MarkerEdgeColor','r')
```



Circle the points which are not filtered out.

```
geoshow(newlat,newlon,'DisplayType','point','Marker','o',...  
        'MarkerEdgeColor','y')
```

Input Arguments

lat — Latitude values

numeric array

Latitude values, specified as a numeric array.

Data Types: single | double

lon — Longitude values

numeric array

Longitude values, specified as a numeric array.

Data Types: `single` | `double`

Z — Filter

numeric array

Filter, specified as a numeric array.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64` | `logical`

R — Spatial referencing information

geographic raster reference object | referencing vector | referencing matrix

Spatial referencing information, specified as a geographic raster reference object, a referencing vector, or a referencing matrix.

If R is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z)`.

If R is a referencing vector, it must be a 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If R is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to or from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If R is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. Nearest-neighbor interpolation is used by default. NaN is returned for points outside the grid limits or for which `lat` or `lon` contain NaN. All angles are in units of degrees.

Data Types: `double`

allowed — Allowed values

numeric array or character vector

Allowed values, specified as a numeric array or character vector.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64` | `logical` | `char`

Output Arguments

latout — Latitudes of filtered points

numeric array

Latitudes of filtered points, returned as a numeric array.

lonout — Longitudes of filtered points

numeric array

Longitudes of filtered points, returned as a numeric array.

indx — Indices of filtered points

numeric array

Indices of filtered points, returned as a numeric array.

See Also

hista | histr | imbedm

Introduced before R2006a

findm

Latitudes and longitudes of nonzero data grid elements

Syntax

```
[lat,lon] = findm(Z,R)
[lat,lon] = findm(latz,lonz,Z)
[lat,lon,val] = findm(...)
mat = findm(...)
```

Description

`[lat,lon] = findm(Z,R)` computes the latitudes and longitudes of the nonzero elements of a regular data grid, `Z`. `R` can be a geographic raster reference object, a referencing vector, or a referencing matrix.

If `R` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z)`.

If `R` is a referencing vector, it must be a 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If `R` is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to or from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If `R` is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. Nearest-neighbor interpolation is used by default. NaN is returned for points outside the grid limits or for which `lat` or `lon` contain NaN. All angles are in units of degrees.

`[lat,lon] = findm(latz,lonz,Z)` returns the latitudes and longitudes of the nonzero elements of a geolocated data grid `Z`, which is an `M`-by-`N` logical or numeric

array. Typically `latz` and `lonz` are M-by-N latitude-longitude arrays, but `latz` may be a latitude vector of length M and `lonz` may be a longitude vector of length N.

`[lat,lon,val] = findm(...)` returns the values of the nonzero elements of Z, in addition to their locations.

`mat = findm(...)` returns a single output, where `mat = [lat lon]`.

This function works in two modes: with a regular data grid and with a geolocated data grid.

Examples

The data grid can be the result of a logical operation. For instance, you can find all locations with elevations greater than 5500 meters.

```
load topo
[lat, lon] = findm((topo>5500),topolegend);
[lat lon]
```

```
ans =
    34.5000    79.5000
    34.5000    80.5000
    30.5000    84.5000
    28.5000    86.5000
```

These points are in the Himalayas. Find the grid values at these locations with `setpostn`:

```
heights = topo(setpostn(topo,topolegend,lat,lon))
```

```
heights =
    5559
    5515
    5523
    5731
```

Use a regular data grid to retrieve the elevations from `setpostn`.

See Also

`find`

Introduced before R2006a

fipsname

Read Federal Information Processing Standard (FIPS) name file used with TIGER thinned boundary files

Note `fipsname` will be removed in a future release. More recent TIGER/Line data sets are available in shapefile format and can be imported using `shapefile`.

Syntax

```
struc = fipsname
struc = fipsname(filename)
```

Description

`struc = fipsname` opens a file selection window to pick the file, reads the FIPS codes, and returns them in a structure.

`struc = fipsname(filename)` reads the specified file.

Background

The TIGER thinned boundary files provided by the U.S. Census use FIPS codes to identify geographic entities. This function reads the FIPS files as provided with the TIGER files. These files generally have names of the format `_name.dat`.

Examples

```
struc = fipsname('st_name.dat')

struc =
1x57 struct array with fields:
    name
```

```
      id
s(1)
ans =
  name: 'Alabama'
  id: 1
```

Tips

The FIPS name files, along with TIGER thinned boundary files, are available over the Internet.

Introduced before R2006a

firstCornerX

Package: map.rasterref

Return world x -coordinate of map raster index (1,1)

Syntax

`x = firstCornerX(R)`

Description

`x = firstCornerX(R)` returns the world x -coordinate of the outermost corner of the first cell (1,1) of map raster R.

Input Arguments

R — Map raster

MapCellsReference or MapPostingsReference object

Map raster, specified as a MapCellsReference or MapPostingsReference object.

Output Arguments

x — World x -coordinate

numeric scalar

World x -coordinate, returned as a numeric scalar.

Data Types: double

See Also

firstCornerY

Introduced in R2013b

firstCornerY

Package: map.rasterref

Return world y-coordinate of map raster index (1,1)

Syntax

```
y = firstCornerY(R)
```

Description

`y = firstCornerY(R)` returns the world y-coordinate of the outermost corner of the first cell (1,1) of map raster R.

Input Arguments

R — Map raster

MapCellsReference or MapPostingsReference object

Map raster, specified as a MapCellsReference or MapPostingsReference object.

Output Arguments

y — World y-coordinate

numeric scalar

World y-coordinate, returned as a numeric scalar.

Data Types: double

See Also

firstCornerX

Introduced in R2013b

flat2ecc

Eccentricity of ellipse from flattening

Note Support for nonscalar input, including the special two-column syntax described below, will be removed in a future release.

Syntax

```
ecc = flat2ecc(f)
ecc = flat2ecc(f)
```

Description

`ecc = flat2ecc(f)` computes the eccentricity of an ellipse (or ellipsoid of revolution) given its flattening `f`. Except when the input has 2 columns (or is a row vector), each element is assumed to be a flattening and the output `ecc` has the same size as `f`.

`ecc = flat2ecc(f)`, where `f` has two columns (or is a row vector), assumes that the second column is a flattening, and a column vector is returned.

See Also

`axes2ecc` | `ecc2flat` | `n2ecc`

Introduced before R2006a

flatearthpoly

Insert points along date line to pole

Syntax

```
[latf,lonf] = flatearthpoly(lat,lon)
[latf,lonf] = flatearthpoly(lat,lon,longitudeOrigin)
```

Description


`[latf,lonf] = flatearthpoly(lat,lon)` trims NaN-separated polygons specified by the latitude and longitude vectors `lat` and `lon` to the limits `[-180 180]` in longitude and `[-90 90]` in latitude, inserting straight segments along the +/- 180-degree meridians and at the poles. Inputs and outputs are in degrees.

`[latf,lonf] = flatearthpoly(lat,lon,longitudeOrigin)` centers the longitude limits on the longitude specified by the scalar longitude `longitudeOrigin`.

Examples


Vector data for geographic objects that encompass a pole will inevitably encounter or cross the date line. While the toolbox properly displays such polygons, they can cause problems for functions like the polygon intersection and Boolean operations that work with Cartesian coordinates. When these polygons are treated as Cartesian coordinates, the date line crossing results in a spurious line segment, and the polygon displayed as a patch does not have the interior filled correctly.

```
antarctica = shaperead('landareas', 'UseGeoCoords', true,...
    'Selector', {@(name) strcmp(name,'Antarctica'), 'Name'});
figure; plot(antarctica.Lon, antarctica.Lat); ylim([-100 -60])
```



The polygons can be reformatted more appropriately for Cartesian coordinates using the `flatearthpoly` function. The result resembles a map display on a cylindrical projection. The polygon meets the date line, drops down to the pole, sweeps across the longitudes at the pole, and follows the date line up to the other side of the date line crossing.

```
[latf, lonf] = flatearthpoly(antarctica.Lat', antarctica.Lon');  
figure; mapshow(lonf, latf, 'DisplayType', 'polygon')  
ylim([-100 -60])  
xlim([-200 200])  
axis square
```



Tips

The polygon topology for the input vectors must be valid. This means that vertices for outer rings (main polygon or “island” polygons) must be in clockwise order, and any inner rings (“lakes”) must run in counterclockwise order for the function to work properly. You can use the `ispolycw` function to check whether or not your `lat`, `lon` vectors meet this criterion, and the `poly2cw` and `poly2ccw` functions to correct any that run in the wrong direction.

See Also

`ispolycw` | `maptrimp` | `poly2ccw` | `poly2cw`

Introduced before R2006a

forward

Package: map.geodesy

Convert geodetic latitude to authalic, conformal, isometric, or rectifying latitude

Syntax

```
lat = forward(converter,phi)
lat = forward(converter,phi,angleUnit)
```

Description

`lat = forward(converter,phi)` returns the authalic, conformal, isometric, or rectifying latitude coordinates corresponding to geodetic latitude coordinates `phi`.

`lat = forward(converter,phi,angleUnit)` specifies the units of input `phi`.

Examples

Convert Geodetic Latitude to Authalic Latitude

```
phi = [-90 -67.5 -45 -22.5 0 22.5 45 67.5 90];
conv = map.geodesy.AuthalicLatitudeConverter(wgs84Ellipsoid);
beta = forward(conv,phi)

beta =

-90.0000 -67.4092 -44.8717 -22.4094          0 22.4094 44.8717 67.4092 90
```

Convert Geodetic Latitude to Isometric Latitude

```
phi = [-90 -67.5 -45 -22.5 0 22.5 45 67.5 90];
conv = map.geodesy.IsometricLatitudeConverter(wgs84Ellipsoid);
psi = forward(conv,phi)
```

```
psi =
```

```
-Inf -1.6087 -0.8766 -0.4006 0 0.4006 0.8766 1.6087
```

Convert Geodetic Latitude to Rectifying Latitude, in Radians

```
phi = [-90 -67.5 -45 -22.5 0 22.5 45 67.5 90];
phirad = deg2rad(phi);
conv = map.geodesy.RectifyingLatitudeConverter(wgs84Ellipsoid);
mu = forward(conv,phirad,'radians')
```

```
mu =
```

```
-90.0000 -67.3978 -44.8557 -22.3981 0 22.3981 44.8557 67.3978 90
```

Input Arguments

converter — Latitude converter

`AuthalicLatitudeConverter`, `ConformalLatitudeConverter`, `IsometricLatitudeConverter`, or `RectifyingLatitudeConverter` object

Latitude converter, specified as an `AuthalicLatitudeConverter`, `ConformalLatitudeConverter`, `IsometricLatitudeConverter`, or `RectifyingLatitudeConverter` object.

phi — Geodetic latitude coordinates

numeric scalar, vector, matrix, or N-D array

Geodetic latitude coordinates, specified as a numeric scalar value, vector, matrix, or N-D array. If `angleUnit` is not supplied, `phi` is in degrees. Otherwise, values of `phi` must be consistent with the units of `angleUnit`.

Data Types: `single` | `double`

angleUnit — Unit of geodetic latitude coordinates

'degrees' (default) | 'radians'

Units of geodetic latitude coordinates, specified as 'degrees' or 'radians'.

Output Arguments

lat — Converted latitude coordinates

numeric scalar, vector, matrix, or N-D array

Converted latitude coordinates, returned as a numeric scalar, vector, matrix, or N-D array. `lat` is the same size as `phi`.

The interpretation of `lat` depends on the latitude converter. If the conversion is:

- authalic, `lat` represents the variable β (beta), and has the same units as `phi`.
- conformal, `lat` represents χ (chi), and has the same units as `phi`.
- isometric, `lat` represents ψ (psi). `lat` is a dimensionless number and does not have an angle unit.
- rectifying, `lat` represents μ (mu), and has the same units as `phi`.

See Also

`inverse`

Introduced in R2013a

framem

Toggle and control display of map frame

Syntax

```
framem  
framem('on')  
framem('off')  
framem('reset')  
framem(linespec)  
framem(PropertyName,PropertyValue,...)
```

Description

`framem` toggles the visibility of the map frame by setting the map axes property `Frame` to 'on' or 'off'. The default setting for map axes is 'off'.

`framem('on')` sets the map axes property `Frame` to 'on'.

`framem('off')` sets the map axes property `Frame` to 'off'. When called with the value 'off', the map axes property `Frame` is set to 'off'.

`framem('reset')` resets the entire frame using the current properties. This is essentially a *refresh* option.

`framem(linespec)` sets the map axes `FEdgeColor` property to the color component of any MATLAB `linespec`.

`framem(PropertyName,PropertyValue,...)` sets the appropriate map axes properties to the desired values. These property names and values are described on the `axesm` reference page.

Tips

- You can also create or alter map frame properties using the `axesm` or `setm` functions.
- By default the Clipping property is set to 'off'. Override this setting with the following code:

```
hgrat = gridm('on');  
set(hgrat,'Clipping','on')
```

See Also

`axesm` | `setm`

Introduced before R2006a

fromDegrees

Convert angles from degrees

Syntax

```
[angle1, angle2, ...] =  
fromDegrees(toUnits, angle1InDegrees, angle2InDegrees, ...)
```

Description

[angle1, angle2, ...] =
fromDegrees(toUnits, angle1InDegrees, angle2InDegrees, ...) converts
angle1InDegrees, angle2InDegrees, ... from degrees to the output angle units
specified by toUnits. The value of toUnits can be either 'degrees' or 'radians'
and may be abbreviated. The inputs angle1InDegrees, angle2InDegrees, ... and
their corresponding outputs are numeric arrays of various sizes, with size(angleN)
matching size(angleNInDegrees).

See Also

deg2rad | fromRadians | toDegrees | toRadians

Introduced in R2007b

fromRadians

Convert angles from radians

Syntax

```
[angle1, angle2, ...] =  
fromRadians(toUnits, angle1InRadians, angle2InRadians, ...)
```

Description

```
[angle1, angle2, ...] =  
fromRadians(toUnits, angle1InRadians, angle2InRadians, ...) converts  
angle1InRadians, angle2InRadians, ... from radians to the angle units specified  
by toUnits. The value of toUnits can be either 'degrees' or 'radians' and may be  
abbreviated. The inputs angle1InRadians, angle2InRadians, ... and their  
corresponding outputs are numeric arrays of various sizes, with size(angleN)  
matching size(angleNInRadians).
```

See Also

[fromDegrees](#) | [rad2deg](#) | [toDegrees](#) | [toRadians](#)

Introduced in R2007b

gc2sc

Center and radius of great circle

Syntax

```
[lat,lon,radius] = gc2sc(lat0,lon0,az)
[lat,lon,radius] = gc2sc(lat0,lon0,az,angleunits)
mat = gc2sc(...)
```

Description

`[lat,lon,radius] = gc2sc(lat0,lon0,az)` converts a great circle from great circle notation (i.e., lat, lon, azimuth, where (lat, lon) is on the circle) to small circle notation (i.e., lat, lon, radius, where (lat, lon) is the center of the circle and the radius is 90 degrees, which is a definition of a great circle). A great circle has two centers and one is chosen arbitrarily. The other is its antipode. All inputs and outputs are in units of degrees.

`[lat,lon,radius] = gc2sc(lat0,lon0,az,angleunits)` where `angleunits` specifies the units of the inputs and outputs, either 'degrees' or 'radians'.

`mat = gc2sc(...)` returns a single output, where `mat = [lat lon radius]`.

Examples

Represent a great circle passing through (25°S,70°W) on an azimuth of 45° as a small circle:

```
[lat,lon,radius] = gc2sc(-25,-70,45)
```

```
lat =
    -39.8557
```

```
lon =
    42.9098
```



```
radius =  
    90
```

A great circle always bisects the sphere. As a demonstration of this statement, consider the Equator, which passes through any point with a latitude of 0° and proceeds on an azimuth of 90° or 270° . Represent the Equator as a small circle:

```
[lat,lon,radius] = gc2sc(0,-70,270)
```

```
lat =
```

```
    90
```

```
lon =
```

```
    0
```

```
radius =
```

```
    90
```

Not surprisingly, the small circle is centered on the North Pole. As always at the poles, the longitude is arbitrary because of the convergence of the meridians.

Note that the center coordinates returned by this function always lead to one of two possibilities. Since the great circle bisects the sphere, the antipode of the returned point is also a center with a radius of 90° . In the above example, the South Pole would also be a suitable center for the Equator in a small circle.

Definitions

Great and Small Circles

A *small circle* is the intersection of a plane with the surface of a sphere. A *great circle* is a small circle with a radius of 90° .

See Also

[antipode](#) | [crossfix](#) | [gcxgc](#) | [gcxsc](#) | [rhxrh](#)

Introduced before R2006a

gcm

Current map projection structure

Syntax

```
mstruct = gcm  
mstruct = gcm(hndl)
```

Description

`mstruct = gcm` returns the map axes *map structure*, which contains the settings for all the current map axes properties.

`mstruct = gcm(hndl)` specifies the map axes by axes handle.

Examples

Establish a map axes with default values, then look at the structure:

```
axesm mercator  
mstruct = gcm  
  
mstruct =  
    mapprojection: 'mercator'  
           zone: []  
    angleunits: 'degrees'  
           aspect: 'normal'  
    falsenorthing: 0  
    falseeastng: 0  
    fixedorient: []  
           geoid: [1 0]  
    maplatlimit: [-86 86]  
    maplonlimit: [-180 180]  
    mapparallels: 0  
           nparallels: 1  
           origin: [0 0 0]
```

```
scalefactor: 1
  trimlat: [-86 86]
  trimlon: [-180 180]
  frame: 'off'
  ffill: 100
  fedgecolor: [0 0 0]
  ffacecolor: 'none'
  flatlimit: [-86 86]
  flinewidth: 2
  flonlimit: [-180 180]
  grid: 'off'
  galtitude: Inf
  gcolor: [0 0 0]
  glinestyle: ':'
  glinewidth: 0.5000
mlineexception: []
  mlinefill: 100
  mlinelimit: []
  mlinelocation: 30
  mlinevisible: 'on'
plineexception: []
  plinefill: 100
  plinelimit: []
  plinelocation: 15
  plinevisible: 'on'
  fontangle: 'normal'
  fontcolor: [0 0 0]
  fontname: 'Helvetica'
  fontsize: 10
  fontunits: 'points'
  fontweight: 'normal'
  labelformat: 'compass'
  labelrotation: 'off'
  labelunits: 'degrees'
meridianlabel: 'off'
mlabellocation: 30
mlabelparallel: 86
  mlabelround: 0
  parallellabel: 'off'
plabellocation: 15
plabelmeridian: -180
  plabelround: 0
```

Tips

You create map structure properties with the `axesm` function. You can query them with the `getm` function and modify them with the `setm` function.

See Also

`axesm` | `getm` | `setm`

Introduced before R2006a

gcpmap

Current mouse point from map axes

Syntax

```
pt = gcpmap
pt = gcpmap(hndl)
```

Description

`pt = gcpmap` returns the current point (the location of last button click) of the current map axes in the form [latitude longitude z-altitude].

`pt = gcpmap(hndl)` specifies the map axes in question by its handle.

Examples

Set up a map axes with a graticule and display a world map:

```
axesm robinson
gridm on
geoshow('landareas.shp')
```


Click somewhere near Boston, Massachusetts to obtain a current point:

```
pt = gcpmap
```

```
pt =
    44.171    -69.967         2
    44.171    -69.967         0
```

```
whos
```

| Name | Size | Bytes | Class | Attributes |
|------|------|-------|--------------|------------|
| pt | 2x3 | 48 | double array | |



Tips

`gcpmap` works much like the standard MATLAB function `get(gca, 'CurrentPoint')`, except that the returned matrix is in `[lat lon z]`, not `[x y z]`.

You must use `view(2)` and an ordinary projection (not the Globe projection) when working with the `gcpmap` function.

The `CurrentPoint` property is updated whenever a button-click event occurs in a MATLAB figure window. The pointer does not have to be within the axes, or even the figure window. Coordinates with respect to the requested axes are returned regardless of the pointer location. Likewise, `gcpmap` will return values that may look reasonable whether the current point is within the graticule bounds or not, and thus must be used with care.

See Also

`inputm`

Introduced before R2006a

gcwaypts

Equally spaced waypoints along great circle

Syntax

```
[lat,lon] = gcwaypts(lat1,lon1,lat2,lon2)
[lat,lon] = gcwaypts(lat1,lon1,lat2,lon2,nlegs)
pts = gcwaypts(lat1,lon1,lat2,lon2...)
```

Description

`[lat,lon] = gcwaypts(lat1,lon1,lat2,lon2)` returns the coordinates of equally spaced points along a great circle path connecting two endpoints, `(lat1,lon1)` and `(lat2,lon2)`.

`[lat,lon] = gcwaypts(lat1,lon1,lat2,lon2,nlegs)` specifies the number of equal-length track legs to calculate. `nlegs+1` output points are returned, since a final endpoint is required. The default number of legs is 10.

`pts = gcwaypts(lat1,lon1,lat2,lon2...)` packs the outputs, which are otherwise two-column vectors, into a two-column matrix of the form `[latitude longitude]`. This format for successive waypoints along a navigational track is called *navigational track format* in this guide. See the `navigational track format` reference page in this section for more information.

Background

This is a navigational function. It assumes that all latitudes and longitudes are in degrees.


In navigational practice, great circle paths are often approximated by rhumb line segments. This is done to come reasonably close to the shortest distance between points without requiring course changes too frequently. The `gcwaypts` function provides an easy means of finding waypoints along a great circle path that can serve as endpoints for rhumb line segments (track legs).

Examples

Determine Equally Spaced Points Along a Great Circle Path

Imagine you own a sailing yacht and are planning a voyage from North Point, Barbados (13.33° N,59.62°W), to Brest, France (48.36°N,4.49°W). Divide the track into three equal-length segments.

```
figure('color','w');
ha = axesm('mapproj','mercator',...
    'maplatlim',[10 55],'maplonlim',[-80 10],...
    'MLineLocation',15,'PLineLocation',15);
axis off, gridm on, framem on;
% Load coastline data and plot it in the figure.
load coastlines;
hg = geoshow(coastlat,coastlon,'displaytype','line','color','b');
% Define point locations for Barbados and Brest
barbados = [13.33 -59.62];
brest = [48.36 -4.49];
% Calculate the waypoints along the path.
[l,g] = gcwaypts(barbados(1),barbados(2),brest(1),brest(2),3);
geoshow(l,g,'displaytype','line','color','r',...
    'markeredgecolor','r','markerfacecolor','r','marker','o');
geoshow(barbados(1),barbados(2),'DisplayType','point',...
    'markeredgecolor','k','markerfacecolor','k','marker','o')
geoshow(brest(1),brest(2),'DisplayType','point',...
    'markeredgecolor','k','markerfacecolor','k','marker','o')
```



See Also

`dreckon` | `legs` | `navfix` | `track`

Introduced before R2006a

gcxgc

Intersection points for pairs of great circles

Syntax

```
[lat,lon] = gcxgc(lat1,lon1,az1,lat2,lon2,az2)
[lat,lon] = gcxgc(lat1,lon1,az1,lat2,lon2,az2,units)
latlon = gcxgc( ___ )
```

Description

`[lat,lon] = gcxgc(lat1,lon1,az1,lat2,lon2,az2)` returns in `lat` and `lon` the locations where pairs of great circles intersect. The great circles are defined using *great circle notation*, which consists of a point on the great circle and the azimuth at that point along which the great circle proceeds. For example, the first great circle in a pair would pass through the point `(lat1,lon1)` with an azimuth of `az1` (in angular units).

For any pair of great circles, there are two possible intersection conditions: the circles are identical or they intersect exactly twice on the sphere.

`[lat,lon] = gcxgc(lat1,lon1,az1,lat2,lon2,az2,units)` specifies the angular units used for all inputs, where `units` is any valid angular unit.

`latlon = gcxgc(___)` returns a single output consisting of the concatenated latitude and longitude coordinates of the great circle intersection points.

Examples

Find Intersection Points of Two Great Circles

Given a great circle passing through $(10^{\circ}\text{N}, 13^{\circ}\text{E})$ and proceeding on an azimuth of 10° , where does it intersect with a great circle passing through $(0^{\circ}, 20^{\circ}\text{E})$, on an azimuth of -23° (that is, 337°)?

```
[newlat,newlon] = gcxgc(10,13,10,0,20,-23)
```

```
newlat =  
    14.3105  -14.3105
```

```
newlon =  
    13.7838  -166.2162
```

Note that the two intersection points are always antipodes of each other. As a simple example, consider the intersection points of two meridians, which are just great circles with azimuths of 0° or 180° :

```
[newlat,newlon] = gcxgc(10,13,0,0,20,180)
```

```
newlat =  
    -90     90
```

```
newlon =  
     0    180
```

The two meridians intersect at the North and South Poles, which is exactly correct.

Input Arguments

lat1, lon1 — Coordinate of point on first great circle

numeric scalar | n -element numeric vector

Latitude or longitude coordinate of a point on the first great circle in each pair, specified as one of these values.

- A numeric scalar to find the intersection of a single pair of great circles.
- A n -element numeric vector to find the intersection of n pairs of great circles.

`lat1` and `lon1` must have the same length.

Example: 10

Example: [-10 20 90 -45]

azi — Azimuth of first great circle

positive numeric scalar | n -element vector of positive numbers

Azimuth of the first great circle of each pair, in angular units, specified as one of these values.

- A positive numeric scalar to find the intersection of a single pair of great circles.
- A n -element vector of positive numbers to find the intersection of n pairs of great circles. The length of `az1` matches the length of `lat1` and `lon1`.

Example: 20

Example: [20 10 45 45]

lat2, lon2 — Coordinate of point on second great circle

numeric scalar | numeric vector

Latitude or longitude coordinate of a point on the second great circle in each pair, specified as one of these values.

- A numeric scalar to find the intersection of a single pair of great circles.
- A n -element numeric vector to find the intersection of n pairs of great circles.

`lat2` and `lon2` must have the same length as `lat1` and `lon1`.

Example: 3

Example: [3 30 85 -45]

az2 — Azimuth of second great circle

positive numeric scalar | n -element vector of positive numbers

Azimuth of the second great circle of each pair, in angular units, specified as one of these values.

- A positive numeric scalar to find the intersection of a single pair of great circles.
- A n -element vector of positive numbers to find the intersection of n pairs of great circles. The length of `az2` matches the length of `lat2` and `lon2`.

Example: 15

Example: [15 15 45 50]

units — Angular units

'degrees' (default) | 'radians'

Angular units, specified as 'degrees' or 'radians'.

Output Arguments

lat, lon — Coordinates of great circle intersections

2-element vector | n -by-2 matrix

Coordinates of great circle intersections, returned as one of the following.

- 2-element vector when you find the intersection of a single pair of great circles.
- n -by-2 matrix when when you find the intersection of n pairs of great circles.

If a pair of great circles are identical, then `gcxgc` displays a warning and returns NaNs for the latitude and longitude coordinates of the intersection points.

latlon — Concatenated coordinates of great circle intersections

4-element vector | n -by-4 matrix

Concatenated coordinates of great circle intersections, returned as one of the following. This output is identical to `[lat lon]`.

- 4-element vector when you find the intersection of a single pair of great circles.
- n -by-4 matrix when you find the intersection of n pairs of great circles.

If a pair of great circles are identical, then `gcxgc` displays a warning and returns NaNs for the latitude and longitude coordinates of the intersection points.

See Also

`antipode` | `crossfix` | `gc2sc` | `gcxsc` | `polyxpoly` | `rhxrh` | `scxsc`

Introduced before R2006a

gcxsc

Intersection points for great and small circle pairs

Syntax

```
[newlat,newlon] = gcxsc(gclat,gclon,gcaz,sclat,sclon,scrangle)
[newlat,newlon] = gcxsc(..., units)
```

Description

`[newlat,newlon] = gcxsc(gclat,gclon,gcaz,sclat,sclon,scrangle)` returns the points of intersection of a great circle in *great circle notation* followed by a small circle in *small circle notation*. For multiple pairings, the inputs must be column vectors. The results are two-column matrices with the coordinates of the intersection points. If the circles do not intersect, or are identical, two NaNs are returned and a warning is displayed. If the two circles are tangent, the single intersection point is repeated twice.

`[newlat,newlon] = gcxsc(..., units)` where `units` specifies the standard angle unit. The default value is 'degrees'.

For a pairing of a great circle with a small circle, there are four possible intersection conditions: the circles are identical (possible because great circles are a subset of small circles), they do not intersect, they are tangent to each other (the small circle interior to the great circle) and hence they intersect once, or they intersect twice.

Great circle notation consists of a point on the great circle and the azimuth at that point along which the great circle proceeds.

Small circle notation consists of a center point and a radius in units of angular arc length.

Examples

Given a great circle passing through (43°N,0°) and proceeding on an azimuth of 10°, where does it intersect with a small circle centered at (47°N,3°E) with an arc length radius of 12°?

```
[newlat,newlon] = gcxsc(43,0,10,47,3,12)
```

```
newlat =  
  35.5068   58.9143
```

```
newlon =  
 -1.6159   5.4039
```

See Also

[crossfix](#) | [gc2sc](#) | [gcxgc](#) | [polyxpoly](#) | [rhxrh](#) | [scxsc](#)

Introduced before R2006a

geocentric2geodeticLat

Convert geocentric to geodetic latitude

Note `geocentric2geodeticLat` will be removed in a future release. Use `geodeticLatitudeFromGeocentric` instead.

Syntax

```
phiI = geocentric2geodeticlat(ecc, phi_g)
```

Description

`phiI = geocentric2geodeticlat(ecc, phi_g)` converts an array of geocentric latitude in radians, `phi_g`, to geodetic latitude in radians, `phiI`, on a reference ellipsoid with first eccentricity `ecc`.

See Also

`geodeticLatitudeFromGeocentric`

Introduced in R2006b

geocentricLatitude

Convert geodetic to geocentric latitude

Syntax

```
psi = geocentricLatitude(phi,F)
psi = geocentricLatitude(phi,F,angleUnit)
```

Description

`psi = geocentricLatitude(phi,F)` returns the geocentric latitude corresponding to geodetic latitude `phi` on an ellipsoid with flattening `F`.

`psi = geocentricLatitude(phi,F,angleUnit)` specifies the units of input `phi` and output `psi`.

Examples

Convert Geodetic Latitude to Geocentric Latitude

Create a reference ellipsoid and then convert the geodetic latitude to geocentric latitude. The reference ellipsoid contains a flattening factor.

```
s = wgs84Ellipsoid;
geocentricLatitude(45, s.Flattening)

ans =

    44.8076
```

Convert Geodetic Latitude Expressed in Radians to Geocentric Latitude

Create a reference ellipsoid and then convert a geodetic latitude expressed in radians to geocentric latitude. The reference ellipsoid contains a flattening factor.

```
s = wgs84Ellipsoid;  
geocentricLatitude(pi/3, s.Flattening, 'radians')  
ans =  
    1.0443
```

Input Arguments

phi — Geodetic latitude of one or more points

scalar value, vector, matrix, or N-D array

Geodetic latitude of one or more points, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

F — Flattening of reference spheroid

scalar

Flattening of reference spheroid, specified as a scalar value.

Data Types: `single` | `double`

angleUnit — Unit of measurement for angle

'degrees' (default) | 'radians'

Unit of measurement for angle, specified as either 'degrees' or 'radians'.

Data Types: `char`

Output Arguments

psi — Geocentric latitudes of one or more points

scalar value, vector, matrix, or N-D array

Geocentric latitudes of one or more points, returned as a scalar value, vector, matrix, or N-D array. Values are in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

See Also

Functions

`geodeticLatitudeFromGeocentric` | `parametricLatitude`

Objects

`AuthalicLatitudeConverter` | `ConformalLatitudeConverter` |
`IsometricLatitudeConverter` | `RectifyingLatitudeConverter`

Introduced in R2013a

geocontourxy

Contour grid in local system with latitude-longitude results

Syntax

```
[contourLines, contourPolygons] = geocontourxy(X, Y, Z, lat0, lon0, h0)
[ ___ ] = geocontourxy( ___ , Name, Value)
```

Description

[contourLines, contourPolygons] = geocontourxy(X, Y, Z, lat0, lon0, h0) returns line and polygon geoshapes containing contour lines and contour fill polygons, respectively. This function is non-graphical. You can plot the return values using geoshow, if desired.

[___] = geocontourxy(___ , Name, Value) specifies name-value pairs that control aspects of the operation. Parameter names can be abbreviated and are case-insensitive.

Examples

Calculate Contour Lines and Polygons for Area Near Hawaii

Define a set of X and Y coordinates and create contour lines and contour polygons.

```
X = -150000:10000:150000;
Y = 0:10000:300000;
[xmesh, ymesh] = meshgrid(X/50000, (Y - 150000)/50000);
Z = 8 + peaks(xmesh, ymesh);
lat0 = dm2degrees([ 21 18]);
lon0 = dm2degrees([-157 49]);
h0 = 300;
levels = 0:2:18;

[contourLines, contourPolygons] = geocontourxy(X, Y, Z, lat0, lon0, h0, ...
    'LevelList', levels, 'XYRotation', 120)
```

```
contourLines =
  8x1 geoshape vector with properties:

  Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
  Vertex properties:
    (8 features concatenated with 7 delimiters)
    Latitude: [1x329 double]
    Longitude: [1x329 double]
    Height: [1x329 double]
  Feature properties:
    ContourLevel: [2 4 6 8 10 12 14 16]

contourPolygons =
  9x1 geoshape vector with properties:

  Collection properties:
    Geometry: 'polygon'
    Metadata: [1x1 struct]
  Vertex properties:
    (9 features concatenated with 8 delimiters)
    Latitude: [1x651 double]
    Longitude: [1x651 double]
    Height: [1x651 double]
  Feature properties:
    LowerContourLevel: [0 2 4 6 8 10 12 14 16]
    UpperContourLevel: [2 4 6 8 10 12 14 16 18]
```

Display Hawaii on a map, add a marker, and then display the polygons returned by `geocontourxy` on the map.


```
figure
usamap([18.5 22.5],[-161 -154])
hawaii = shaperead('usastatehi', 'UseGeoCoords', true,...
    'Selector',{@(name) strcmpi(name,'Hawaii'), 'Name'});
geoshow(hawaii)
geoshow(lat0,lon0, 'DisplayType','point','Marker','o',...
    'MarkerEdgeColor','k','MarkerFaceColor','k','MarkerSize',10)

cmap = parula(1 + length(levels));
for k = 1:length(contourPolygons)
    lat = contourPolygons(k).Latitude;
```

```

lon = contourPolygons(k).Longitude;
geoshow(lat,lon,'Display','polygon',...
         'FaceColor',cmap(k,:), 'FaceAlpha',0.5, 'EdgeColor','none')
end
geoshow(contourLines.Latitude,contourLines.Longitude,'Color','black')

```



Input Arguments

X — X-component of a mesh that locates each element of **Z** in a local x-y plane
vector or matrix

X-component of a mesh that locates each element of *Z* in a local x-y plane, specified as a vector or matrix. `geocontourxy` assumes that units are meters unless you provide a `Spheroid` input, in which case the units of your input must match the `LengthUnit` property of the `Spheroid` object.

Data Types: `single` | `double`

Y — Y-component of a mesh that locates each element of *Z* in a local x-y plane

vector or matrix

Y-component of a mesh that locates each element of *Z* in a local x-y plane. specified as a vector or matrix. `geocontourxy` assumes that units are meters unless you provide a `Spheroid` input, in which case the units of your input must match the `LengthUnit` property of the `Spheroid` object.

Data Types: `single` | `double`

Z — Data to be contoured

2-D array

Data to be contoured, specified as a 2-D array.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64`

lat0 — Geodetic latitude of local origin (reference) point

scalar value in units of degrees

Geodetic latitude of local origin (reference) point, specified as a scalar value in units of degrees.

Data Types: `single` | `double`

lon0 — Geodetic longitude of local origin (reference) point

scalar value in units of degrees

Geodetic longitude of local origin (reference) point, specified as a scalar value in units of degrees.

Data Types: `single` | `double`

h0 — Ellipsoidal height of local origin (reference) point

scalar value

Ellipsoidal height of local origin (reference) point, specified as a scalar value. `geocontourxy` assumes that units are meters unless you provide a `Spheroid` input, in which case the units of your input must match the unit specified in the `LengthUnit` property of the `Spheroid` object.

Data Types: `single` | `double`

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, . . . , NameN, ValueN`.

Example: `[contourLines, contourPolygons] = geocontourxy(X,Y,Z,lat0,lon0,h0,'LevelList',levels,'XYRotation',120)`

LevelList — Contour levels

vector of Z-values

Contour levels, specified as a vector of Z-values. By default, the `geocontourxy` function chooses levels that span the range of values.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64`

XYRotation — Rotation angle of the local x-y system

0 (default) | scalar value in units of degrees

Rotation angle of the local x-y system, measured counterclockwise from the *xEast-yNorth* system, specified as a scalar value in units of degrees.

Data Types: `single` | `double`

Spheroid — Reference spheroid

WGS84 reference ellipsoid (default) | `referenceEllipsoid` | `oblateSpheroid` | `referenceSphere`

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. Use the constructor for one of these three classes, or the `wgs84Ellipsoid` function, to construct a Mapping Toolbox spheroid object. (You cannot directly pass in to `geocontourxy` the name of your spheroid. Instead, pass that name to

referenceEllipsoid or referenceSphere and use the resulting object.) By default, geocontourxy uses the WGS84 reference ellipsoid with units of meters.

Output Arguments

contourLines — Contour lines

line geoshape

Contour lines, returned as a line geoshape with one element per contour level. `Latitude` and `Longitude` properties contain contour line vertices in degrees. The contour level value of the k -th element is stored in the `ContourLevel` feature property of `contourLines(k)`. A third vertex property, `Height`, contains the ellipsoidal height of each vertex. In combination with `Latitude` and `Longitude`, it completes the definition of the 3-D location of the contour line in the plane that contains the local origin and is parallel to the tangent plane at the origin latitude and longitude.

contourPolygons — Contour polygons

polygon geoshape

Contour polygons, returned as a polygon geoshape with one element (contour fill polygon) per contour interval. `Latitude` and `Longitude` properties contain the vertices of the contour fill polygons, specified in degrees. The `LowerContourLevel` and `UpperContourLevel` properties of `contourPolygons(k)` store the limits of the k -th contour interval. As in the case of lines, a third vertex property, `Height`, is included.

See Also

`contourfm` | `contourm` | `enu2geodetic` | `geodetic2enu`

Introduced in R2016a

geodetic2aer

Geodetic to local spherical AER

Syntax

```
[az,elev,slantRange] = geodetic2aer(lat,lon,h,lat0,lon0,h0,spheroid)
[___] = geodetic2aer(___,angleUnit)
```

Description

[az,elev,slantRange] = geodetic2aer(lat,lon,h,lat0,lon0,h0,spheroid) returns coordinates in a local spherical system corresponding to geodetic coordinates lat, lon, h. spheroid is an instance of a reference spheroid object. Any of the first six numeric input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

[___] = geodetic2aer(___,angleUnit) adds angleUnit which specifies the units of inputs lat, lon, lat0, lon0, and outputs az, elev.

Examples

Zermatt to the Matterhorn

Compute the azimuth (in degrees), elevation angle (in degrees), and line of sight distance from Zermatt, Switzerland to the summit of the Matterhorn (Monte Cervino). All distances and lengths are in meters.

Origin (reference point): Zermatt.

```
fmt = get(0,'Format');
format short g
```

```
lat0 = dm2degrees([46 1])    % convert degree-minutes to degrees
lon0 = dm2degrees([ 7 45])
```

```
hOrthometric0 = 1620;  
hGeoid = 53;  
h0 = hOrthometric0 + hGeoid
```

```
lat0 =  
    46.017
```

```
lon0 =  
    7.75
```

```
h0 =  
    1673
```

Point of Interest: Summit of Matterhorn.

```
lat = dms2degrees([45 58 35])  
lon = dms2degrees([ 7 39 30])  
hOrthometric = 4478;  
hGeoid = 53;  
h = hOrthometric + hGeoid
```

```
lat =  
    45.976
```

```
lon =  
    7.6583
```

```
h =  
    4531
```

Azimuth, elevation angle, and slant range (line of sight distance) from Zermatt to Matterhorn summit.

```
spheroid = referenceEllipsoid('WGS 84')
```

```
[az,elev,slantRange] = geodetic2aer( ...
    lat,lon,h,lat0,lon0,h0,spheroid)

format(fmt)

spheroid =

referenceEllipsoid with defining properties:

    Code: 7030
    Name: 'World Geodetic System 1984'
    LengthUnit: 'meter'
    SemimajorAxis: 6378137
    SemiminorAxis: 6356752.31424518
    InverseFlattening: 298.257223563
    Eccentricity: 0.0818191908426215

and additional properties:

    Flattening
    ThirdFlattening
    MeanRadius
    SurfaceArea
    Volume

az =

    237.8

elev =

    18.755

slantRange =

    8871.7
```

Input Arguments

lat — Geodetic latitudes

scalar value | vector | matrix | N-D array

Geodetic latitudes of one or more points, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon — Longitudes

scalar value | vector | matrix | N-D array

Longitudes of one or more points, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

h — Ellipsoidal heights

scalar value | vector | matrix | N-D array

Ellipsoidal heights of one or more points, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the `spheroid` object.

Data Types: `single` | `double`

lat0 — Geodetic latitude of local origin

scalar value | vector | matrix | N-D array

Geodetic latitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lat0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon0 — Longitude of local origin

scalar value | vector | matrix | N-D array

Longitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lon0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

h0 — Ellipsoidal height of local origin

scalar value | vector | matrix | N-D array

Ellipsoidal height of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `h0` is scalar, but it need not be. (It may refer to a moving platform, for example). Units are determined by the `LengthUnit` property of the spheroid input.

Data Types: `single` | `double`

spheroid — Reference spheroid

`referenceEllipsoid` | `oblateSpheroid` | `referenceSphere`

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. To create a spheroid object, use the creation function specific to the object, or the `wgs84Ellipsoid` function.

Example: `spheroid = referenceEllipsoid('GRS 80');`

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: `char` | `string`

Output Arguments

az — Azimuth angles

scalar value | vector | matrix | N-D array

Azimuth angles in the local spherical system, returned as a scalar value, vector, matrix, or N-D array. Azimuths are measured clockwise from north. Units are determined by the input argument `angleUnit`, if supplied; values are in degrees, otherwise. When in degrees, they lie in the half-open interval [0 360).

elev — Elevation angles

scalar value | vector | matrix | N-D array

Elevation angles in the local spherical system, returned as a scalar value, vector, matrix, or N-D array. Elevations are with respect to a plane perpendicular to the spheroid surface

normal. Units determined by the input argument `angleUnit`, if supplied; values are in degrees, otherwise. When in degrees, they lie in the closed interval [-90 90].

s`lantRange` — Distances from local origin

scalar value | vector | matrix | N-D array

Distances from origin in the local spherical system, returned as a scalar value, vector, matrix, or N-D array. The straight-line, 3-D Cartesian distance is computed. Units are determined by the `LengthUnit` property of the `spheroid` input.

See Also

`aer2geodetic` | `ecef2aer` | `geodetic2enu` | `geodetic2ned`

Introduced in R2012b

geodetic2ecef

Transform geodetic to geocentric (ECEF) coordinates

Syntax

```
[X,Y,Z] = geodetic2ecef(spheroid,lat,lon,h)
```

```
[X,Y,Z] = geodetic2ecef( ____,angleUnit)
```

```
[X,Y,Z] = geodetic2ecef(lat,lon,h,spheroid)
```

Description

`[X,Y,Z] = geodetic2ecef(spheroid,lat,lon,h)` transforms geodetic point locations specified by the geodetic coordinate arrays `lat` (geodetic latitude), `lon` (longitude), and `h` (ellipsoidal height) to geocentric Earth-Centered Earth-Fixed (ECEF) Cartesian coordinates `x`, `y`, and `z`. The geodetic coordinates refer to the reference body specified by the spheroid object, `spheroid`.

`[X,Y,Z] = geodetic2ecef(____,angleUnit)` where `angleUnit` specifies the units of the latitude and longitude coordinates, either 'degrees' or 'radians'.

`[X,Y,Z] = geodetic2ecef(lat,lon,h,spheroid)` This syntax is supported but not recommended. `lat` and `lon` must be in radians. `spheroid` can be either a spheroid or an ellipsoid vector of the form: `[semimajor_axis, eccentricity]`. In this case, `h` must use the same units as the semimajor axis. `X`, `Y`, and `Z` will be expressed in these units also.

Examples

Convert Geodetic Coordinates to Geocentric Coordinates

Convert the geodetic coordinates for Paris, France (48 degrees 51 minutes 24 seconds North, 2 degrees 21 minutes 03 seconds East) to geocentric Earth-Centered Earth-Fixed (ECEF) Cartesian coordinates.

```
lat = dms2degrees([48 51 24])  
lat = 48.8567  
lon = dms2degrees([2 21 03])  
lon = 2.3508  
h = 80;  
wgs84 = wgs84Ellipsoid('meters');  
[x,y,z] = geodetic2ecef(wgs84,lat,lon,h)  
x = 4.2010e+06  
y = 1.7246e+05  
z = 4.7801e+06
```

Input Arguments

spheroid — Reference spheroid

referenceEllipsoid | oblateSpheroid | referenceSphere

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. To create a spheroid object, use the creation function specific to the object, or the `wgs84Ellipsoid` function.

Example: `spheroid = referenceEllipsoid('GRS 80');`

lat — Geodetic latitudes

scalar value | vector | matrix | N-D array

Geodetic latitudes of one or more points, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon — Longitudes

scalar value | vector | matrix | N-D array

Longitudes of one or more points, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

h — Ellipsoidal height

numeric array

Ellipsoidal height, specified as a scalar. `h` must be expressed in the same length unit as the spheroid.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64`

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: `char` | `string`

Output Arguments

X — ECEF x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid object.

Y — ECEF y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid object.

Z — ECEF z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the `spheroid` object.

Tips

- The geocentric Cartesian (ECEF) coordinate system is fixed with respect to the Earth, with its origin at the center of the spheroid and its positive x-, y-, and z-axes intersecting the surface at the following points:

| | Latitude | Longitude | Notes |
|--------|-----------------|------------------|-------------------------------|
| x-axis | 0 | 0 | Equator at the Prime Meridian |
| y-axis | 0 | 90 | Equator at 90-degrees East |
| z-axis | 90 | 0 | North Pole |

See Also

`ecef2geodetic` | `ecef0ffset` | `oblateSpheroid` | `referenceEllipsoid` | `referenceSphere`

Introduced in R2012b

geodetic2enu

Geodetic to local Cartesian ENU

Syntax

```
[xEast,yNorth,zUp] = geodetic2enu(lat,lon,h,lat0,lon0,h0,spheroid)  
[xEast,yNorth,zUp] = geodetic2enu( ____,angleUnit)
```

Description

`[xEast,yNorth,zUp] = geodetic2enu(lat,lon,h,lat0,lon0,h0,spheroid)` returns coordinates in a local east-north-up (ENU) Cartesian system corresponding to geodetic coordinates `lat`, `lon`, `h`. Any of the first six numeric input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

`[xEast,yNorth,zUp] = geodetic2enu(____,angleUnit)` adds `angleUnit` which specifies the units of inputs `lat`, `lon`, `lat0`, and `lon0`.

Input Arguments

lat — Geodetic latitudes

scalar value | vector | matrix | N-D array

Geodetic latitudes of one or more points, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon — Longitudes

scalar value | vector | matrix | N-D array

Longitudes of one or more points, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

h — Ellipsoidal heights

scalar value | vector | matrix | N-D array

Ellipsoidal heights of one or more points, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the spheroid object.

Data Types: `single` | `double`

lat0 — Geodetic latitude of local origin

scalar value | vector | matrix | N-D array

Geodetic latitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lat0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon0 — Longitude of local origin

scalar value | vector | matrix | N-D array

Longitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lon0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

h0 — Ellipsoidal height of local origin

scalar value | vector | matrix | N-D array

Ellipsoidal height of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `h0` is scalar, but it need not be. (It may refer to a moving platform, for example). Units are determined by the `LengthUnit` property of the spheroid input.

Data Types: `single` | `double`

spheroid — Reference spheroid

`referenceEllipsoid` | `oblateSpheroid` | `referenceSphere`

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. To create a spheroid object, use the creation function specific to the object, or the `wgs84Ellipsoid` function.

Example: `spheroid = referenceEllipsoid('GRS 80');`

angleUnit — Units of angles

`'degrees'` (default) | `'radians'`

Units of angles, specified as `'degrees'` (default), or `'radians'`.

Data Types: `char` | `string`

Output Arguments

xEast — Local ENU x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the local ENU system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid input.

yNorth — Local ENU y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the local ENU system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid input.

zUp — Local ENU z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the local ENU system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid input.

See Also

`ecef2enu` | `enu2geodetic` | `geodetic2aer` | `geodetic2ned`

Introduced in R2012b

geodetic2ned

Geodetic to local Cartesian NED

Syntax

```
[xNorth,yEast,zDown] = geodetic2ned(lat,lon,h,lat0,lon0,h0,spheroid)  
[ ___ ] = geodetic2ned( ___,angleUnit)
```

Description

`[xNorth,yEast,zDown] = geodetic2ned(lat,lon,h,lat0,lon0,h0,spheroid)` transforms point locations from geodetic coordinates (`lat`, `lon`, `h`) to local, north-east-down (NED), Cartesian coordinates (`xNorth`, `yEast`, `zDown`), given a local coordinate system defined by the geodetic coordinates of its origin (`lat0`, `lon0`, `h0`). The geodetic coordinates refer to the reference body specified by the spheroid object, `spheroid`. Each coordinate input argument must match the others in size or be scalar.

`[___] = geodetic2ned(___,angleUnit)` specifies the unit of the latitude and longitude input arguments, `lat`, `lon`, `lat0`, and `lon0`.

Input Arguments

lat — Geodetic latitudes

scalar value | vector | matrix | N-D array

Geodetic latitudes of one or more points, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon — Longitudes

scalar value | vector | matrix | N-D array

Longitudes of one or more points, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

h — Ellipsoidal heights

scalar value | vector | matrix | N-D array

Ellipsoidal heights of one or more points, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the spheroid object.

Data Types: `single` | `double`

lat0 — Geodetic latitude of local origin

scalar value | vector | matrix | N-D array

Geodetic latitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lat0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon0 — Longitude of local origin

scalar value | vector | matrix | N-D array

Longitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lon0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

h0 — Ellipsoidal height of local origin

scalar value | vector | matrix | N-D array

Ellipsoidal height of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `h0` is scalar, but it need not be. (It may refer to a moving platform, for example). Units are determined by the `LengthUnit` property of the spheroid input.

Data Types: `single` | `double`

spheroid — Reference spheroid

`referenceEllipsoid` | `oblateSpheroid` | `referenceSphere`

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. To create a spheroid object, use the creation function specific to the object, or the `wgs84Ellipsoid` function.

Example: `spheroid = referenceEllipsoid('GRS 80');`

angleUnit — Units of angles

`'degrees'` (default) | `'radians'`

Units of angles, specified as `'degrees'` (default), or `'radians'`.

Data Types: `char` | `string`

Output Arguments

xNorth — Local NED x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the local NED system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid input.

yEast — Local NED y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the local NED system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid input.

zDown — Local NED z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the local NED system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid input.

See Also

`ecef2ned` | `geodetic2aer` | `geodetic2enu` | `ned2geodetic`

Introduced in R2012b

geodetic2geocentricLat

Convert geodetic to geocentric latitude

Note `geodetic2geocentricLat` will be removed in a future release. Use `geocentricLatitude` instead.

Syntax

```
phi_g = geodetic2geocentriclat(ecc, phi)
```

Description

`phi_g = geodetic2geocentriclat(ecc, phi)` converts an array of geodetic latitude in radians, `phi`, to geocentric latitude in radians, `phi_g`, on a reference ellipsoid with first eccentricity `ecc`.

See Also

`geocentricLatitude`

Introduced in R2006b

geodeticLatitudeFromGeocentric

Convert geocentric to geodetic latitude

Syntax

```
phi = geodeticLatitudeFromGeocentric(psi,F)
phi = geodeticLatitudeFromGeocentric(psi,F,angleUnit)
```

Description

`phi = geodeticLatitudeFromGeocentric(psi,F)` returns the geodetic latitude corresponding to geocentric latitude `psi` on an ellipsoid with flattening `F`.

`phi = geodeticLatitudeFromGeocentric(psi,F,angleUnit)` specifies the units of input `psi` and output `phi`.

Examples

Convert Geocentric Latitude to Geodetic Latitude

Create a reference ellipsoid.

```
s = wgs84Ellipsoid;
```

Convert the geocentric latitude to geodetic latitude. The reference ellipsoid contains a flattening factor.

```
geodeticLatitudeFromGeocentric(45, s.Flattening)
```

```
ans = 45.1924
```

Convert Geocentric Latitude Expressed in Radians to Geodetic Latitude

Create a reference ellipsoid.

```
s = wgs84Ellipsoid;
```

Convert a geocentric latitude expressed in radians to geodetic latitude. The reference ellipsoid contains a flattening factor.

```
geodeticLatitudeFromGeocentric(pi/3, s.Flattening, 'radians')  
ans = 1.0501
```

Input Arguments

psi — Geocentric latitude of one or more points

scalar value, vector, matrix, or N-D array

Geocentric latitudes of one or more points, returned as a scalar value, vector, matrix, or N-D array. Values are in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

F — Flattening of reference spheroid

scalar

Flattening of reference spheroid, specified as a scalar value.

Data Types: `double`

angleUnit — Unit of measurement for angle

'degrees' (default) | 'radians'

Unit of measurement for angle, specified as either 'degrees' or 'radians'.

Data Types: `char`

Output Arguments

phi — Geodetic latitude of one or more points

scalar value, vector, matrix, or N-D array

Geodetic latitude of one or more points, returned as a scalar value, vector, matrix, or N-D array. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

See Also

Functions

`geocentricLatitude` | `geodeticLatitudeFromParametric`

Objects

`AuthalicLatitudeConverter` | `ConformalLatitudeConverter` |
`IsometricLatitudeConverter` | `RectifyingLatitudeConverter`

geodeticLatitudeFromParametric

Convert parametric to geodetic latitude

Syntax

```
phi = geodeticLatitudeFromParametric(beta,F)
phi = geodeticLatitudeFromParametric(beta,F,angleUnit)
```

Description

`phi = geodeticLatitudeFromParametric(beta,F)` returns the geodetic latitude corresponding to parametric latitude `beta` on an ellipsoid with flattening `F`.

`phi = geodeticLatitudeFromParametric(beta,F,angleUnit)` specifies the units of input `beta` and output `phi`.

Examples

Convert Parametric Latitude to Geodetic Latitude

Create a reference ellipsoid and then convert the parametric latitude to geodetic latitude. The reference ellipsoid contains a flattening factor.

```
s = wgs84Ellipsoid;
geodeticLatitudeFromParametric(45, s.Flattening)
ans =
    45.0962
```

Convert Parametric Latitude Expressed in Radians to Geodetic Latitude

Create a reference ellipsoid and then convert a parametric latitude expressed in radians to geodetic latitude. The reference ellipsoid contains a flattening factor.

```
s = wgs84Ellipsoid;  
geodeticLatitudeFromParametric(pi/3, s.Flattening, 'radians')  
ans =  
    1.0487
```

Input Arguments

beta — Parametric latitude of one or more points

scalar value, vector, matrix, or N-D array

Parametric latitude of one or more points, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

F — Flattening of reference spheroid

scalar

Flattening of reference spheroid, specified as a scalar value.

Data Types: `double`

angleUnit — Unit of measurement for angle

'degrees' (default) | 'radians'

Unit of measurement for angle, specified as either 'degrees' or 'radians'.

Data Types: `char`

Output Arguments

phi — Geodetic latitudes of one or more points

scalar value, vector, matrix, or N-D array

Geodetic latitudes of one or more points, returned as a scalar value, vector, matrix, or N-D array. Values are in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

See Also

Functions

`geodeticLatitudeFromGeocentric` | `parametricLatitude`

Objects

`AuthalicLatitudeConverter` | `ConformalLatitudeConverter` |
`IsometricLatitudeConverter` | `RectifyingLatitudeConverter`

GeographicCellsReference

Reference raster cells to geographic coordinates

Description

A geographic cells raster reference object encapsulates the relationship between a geographic coordinate system and a system of intrinsic coordinates anchored to the columns and rows of a 2-D spatially referenced raster grid or image.

The raster must be sampled regularly in latitude and longitude, and its columns and rows must be aligned with meridians and parallels, respectively. For more information about coordinate systems, see “Intrinsic Coordinate System” on page 1-463.

Creation

You can use any of the following functions to create a `GeographicCellsReference` object to reference a regular raster of cells to geographic coordinates.

- `georefcells` — Create a geographic raster reference object.
- `georasterref` — Convert a world file to a geographic raster reference object.
- `refmatToGeoRasterReference` — Convert a referencing matrix to a geographic raster reference object.
- `refvecToGeoRasterReference` — Convert a referencing vector to a geographic raster reference object.

For example, to construct a geographic raster reference object with default property settings, use this command:

```
R = georefcells()
```

```
R =
```

```
GeographicCellsReference with properties:
```

```
LatitudeLimits: [0.5 2.5]  
LongitudeLimits: [0.5 2.5]
```

```

        RasterSize: [2 2]
    RasterInterpretation: 'cells'
        ColumnsStartFrom: 'south'
        RowsStartFrom: 'west'
    CellExtentInLatitude: 1
    CellExtentInLongitude: 1
    RasterExtentInLatitude: 2
    RasterExtentInLongitude: 2
        XIntrinsicLimits: [0.5 2.5]
        YIntrinsicLimits: [0.5 2.5]
    CoordinateSystemType: 'geographic'
        AngleUnit: 'degree'

```

Properties

LatitudeLimits — Latitude limits of the geographic quadrangle bounding the georeferenced raster

[0.5 2.5] (default) | two-element vector

Latitude limits of the geographic quadrangle bounding the georeferenced raster, specified as a two-element vector of the form [southern_limit northern_limit].

Example: [-90 90]

Data Types: double

LongitudeLimits — Longitude limits of the geographic quadrangle bounding the georeferenced raster

[0.5 2.5] (default) | two-element vector

Longitude limits of the geographic quadrangle bounding the georeferenced raster, specified as a two-element vector of the form [western_limit eastern_limit].

Example: [-100 180]

Data Types: double

RasterSize — Number of rows and columns of the raster or image associated with the referencing object

[2 2] (default) | two-element vector of positive integers

Number of rows and columns of the raster or image associated with the referencing object, specified as a two-element vector, [m n], where m represents the number of rows

and n the number of columns. For convenience, you can assign a size vector having more than two elements. This enables assignments like `R.RasterSize = size(RGB)`, where `RGB` is m -by- n -by-3. In cases like this, the object stores only the first two elements of the size vector and ignores the higher (nonspatial) dimensions.

Example: `[200 300]`

Data Types: `double`

RasterInterpretation — Geometric nature of the raster

`'cells'` (default)

This property is read-only.

Geometric nature of the raster, specified as `'cells'`. The value `'cells'` indicates that the raster comprises a grid of quadrangular cells, and is bounded on all sides by cell edges. For an m -by- n raster, points with an intrinsic x -coordinate of 1 or n or an intrinsic y -coordinate of 1 or m fall within the raster, not on its edges.

Data Types: `char`

AngleUnit — Unit of measurement used for angle-valued properties

`'degree'` (default)

Unit of measurement used for angle-valued properties, specified as `'degree'`.

Cannot be set.

Data Types: `char`

ColumnsStartFrom — Edge from which column indexing starts

`'south'` (default) | `'north'`

Edge from which column indexing starts, specified as `'south'` or `'north'`.

Example: `'south'`

Data Types: `char`

RowsStartFrom — Edge from which row indexing starts

`'west'` (default) | `'east'`

Edge from which row indexing starts, specified as `'west'` or `'east'`.

Example: `'east'`

Data Types: char

CellExtentInLatitude — Extent in latitude of individual cells

1 (default) | positive numeric scalar

Extent in latitude of individual cells, specified as a positive numeric scalar. Distance, in units of latitude, between the northern and southern limits of a single raster cell. The value is the same for all cells in the raster.

Example: 2.5

Data Types: double

CellExtentInLongitude — Extent in longitude of individual cells

1 (default) | positive numeric scalar

Extent in longitude of individual cells, specified as a positive numeric scalar. Distance, in units of longitude, between the western and eastern limits of a single raster cell. The value is always positive, and is the same for all cells in the raster.

Example: 2.5

Data Types: double

RasterExtentInLatitude — Latitude extent ("height") of the quadrangle covered by the raster

2 (default) | positive numeric scalar

This property is read-only.

Latitude extent ("height") of the quadrangle covered by the raster, specified as a positive numeric scalar.

Example: 2

Data Types: double

RasterExtentInLongitude — Longitude extent ("width") of the quadrangle covered by the raster

2 (default) | positive numeric scalar

This property is read-only.

Longitude extent ("width") of the quadrangle covered by the raster, specified as a positive numeric scalar.

Data Types: double

XIntrinsicLimits — Raster limits in intrinsic x coordinates

[0.5 2.5] (default) | two-element row vector of positive integers

This property is read-only.

Raster limits in intrinsic x coordinates, specified as a two-element row vector of positive integers, [xMin xMax]. For an m -by- n raster, XIntrinsicLimits equals [0.5, m + 0.5], because the RasterInterpretation is 'cells'.

Example: [0.5 2.5]

Data Types: double

YIntrinsicLimits — Raster limits in intrinsic y coordinates

[0.5 2.5] (default) | two-element row vector of positive integers

This property is read-only.

Raster limits in intrinsic y coordinates, specified as a two-element row vector of positive integers, [yMin yMax]. For an m -by- n raster, YIntrinsicLimits equals [0.5, n + 0.5], because the RasterInterpretation is 'cells'.

Data Types: double

CoordinateSystemType — Type of coordinate system to which the image or raster is referenced

'geographic' (default)

This property is read-only.

Type of coordinate system to which the image or raster is referenced, specified as 'geographic'.

Data Types: char

Object Functions

| | |
|-----------------------|---|
| contains | Determine if geographic or map raster contains points |
| geographicToDiscrete | Transform geographic to discrete coordinates |
| geographicToIntrinsic | Transform geographic to intrinsic coordinates |
| intrinsicToGeographic | Transform intrinsic to geographic coordinates |

| | |
|------------------------------------|--|
| <code>intrinsicXToLongitude</code> | Convert from intrinsic x to longitude coordinates |
| <code>intrinsicYToLatitude</code> | Convert from intrinsic y to latitude coordinates |
| <code>latitudeToIntrinsicY</code> | Convert from latitude to intrinsic y coordinates |
| <code>longitudeToIntrinsicX</code> | Convert from longitude to intrinsic x coordinates |
| <code>sizesMatch</code> | Determine if geographic or map raster object and image or raster are size-compatible |
| <code>worldFileMatrix</code> | Return world file parameters for transformation |

Definitions

Intrinsic Coordinate System

A 2-D Cartesian system with its x -axis running parallel to the rows of a raster or image and its y -axis running parallel to the columns. x increases by 1 from column to column, and y increases by 1 from row to row.

Mapping Toolbox and Image Processing Toolbox™ use the convention for the location of the origin relative to the raster cells or sampling points such that, at a sample location or at the center of a cell, x has an integer value equal to the column index. Likewise, at a sample location or at the center of a cell, y has an integer value equal to the row index. For details, see Image Coordinate Systems (Image Processing Toolbox).

See Also

Functions

`georasterref` | `georefcells`

Objects

`GeographicPostingsReference` | `MapCellsReference` | `MapPostingsReference`

Introduced in R2013b

GeographicPostingsReference

Reference raster postings to geographic coordinates

Description

A geographic postings raster reference object encapsulates the relationship between a geographic coordinate system and a system of intrinsic coordinates anchored to the columns and rows of a 2-D spatially referenced grid of point samples (or “postings”).

The raster must be sampled regularly in latitude and longitude, and its columns and rows must be aligned with meridians and parallels, respectively. For more information about coordinate systems, see “Intrinsic Coordinate System” on page 1-469.

Creation

You can use any of the following functions to create a `GeographicPostingsReference` object to reference a regular raster of posted samples to geographic coordinates.

- `georefpostings` — Create a geographic raster reference object.
- `georasterref` — Convert a world file to a geographic raster reference object.
- `refmatToGeoRasterReference` — Convert a referencing matrix to a geographic raster reference object.

For example, to construct a geographic raster reference object with default property settings, use this command:

```
R = georefpostings()
```

```
R =
```

```
GeographicPostingsReference with properties:
```

```
LatitudeLimits: [0.5 1.5]  
LongitudeLimits: [0.5 1.5]  
RasterSize: [2 2]  
RasterInterpretation: 'postings'
```

```

        ColumnsStartFrom: 'south'
        RowsStartFrom: 'west'
    SampleSpacingInLatitude: 1
    SampleSpacingInLongitude: 1
    RasterExtentInLatitude: 1
    RasterExtentInLongitude: 1
        XIntrinsicLimits: [1 2]
        YIntrinsicLimits: [1 2]
    CoordinateSystemType: 'geographic'
        AngleUnit: 'degree'

```

Properties

LatitudeLimits — Latitude limits of the geographic quadrangle bounding the georeferenced raster

[0.5 1.5] (default) | two-element vector

Latitude limits of the geographic quadrangle bounding the georeferenced raster, specified as a two-element vector of the form [southern_limit northern_limit].

Example: [-20 70]

Data Types: double

LongitudeLimits — Longitude limits of the geographic quadrangle bounding the georeferenced raster

[0.5 1.5] (default) | two-element vector

Longitude limits of the geographic quadrangle bounding the georeferenced raster, specified as a two-element vector of the form [western_limit eastern_limit].

Example: [-100 180]

Data Types: double

RasterSize — Number of rows and columns of the raster or image associated with the referencing object

[2 2] (default) | two-element vector of positive integers

Number of rows and columns of the raster or image associated with the referencing object, specified as a two-element vector, [m n], where *m* represents the number of rows and *n* the number of columns. For convenience, you can assign a size vector having more than two elements. This enables assignments like `R.RasterSize = size(RGB)`, where

RGB is m -by- n -by-3. In cases like this, the object stores only the first two elements of the size vector and ignores the higher (nonspatial) dimensions.

Example: [200 300]

Data Types: double

RasterInterpretation — Geometric nature of the raster

'postings' (default)

This property is read-only.

Geometric nature of the raster, specified as 'postings'.

The value 'postings' indicates that the raster comprises a grid of sample points, where rows or columns of samples run along the edge of the grid. For an m -by- n raster, points with an intrinsic x -coordinate of 1 or n and/or an intrinsic y -coordinate of 1 or m fall right on an edge (or corner) of the raster.

Data Types: char

AngleUnit — Unit of measurement used for angle-valued properties

'degree' (default)

This property is read-only.

Unit of measurement used for angle-valued properties, specified as 'degree'.

Data Types: char

ColumnsStartFrom — Edge from which column indexing starts

'south' (default) | 'north'

Edge from which column indexing starts, specified as 'south' or 'north'.

Example: 'south'

Data Types: char

RowsStartFrom — Edge from which row indexing starts

'west' (default) | 'east'

Edge from which row indexing starts, specified as 'west' or 'east'.

Example: 'east'

Data Types: char

SampleSpacingInLatitude — North-south distance in latitude between adjacent samples in the raster

1 (default) | positive numeric scalar

North-south distance in latitude between adjacent samples (postings) in the raster, specified as a positive numeric scalar. The value is always positive, and is the constant throughout the raster.

Example: 2.5

Data Types: double

SampleSpacingInLongitude — East-west distance in longitude between adjacent samples in the raster

1 (default) | positive numeric scalar

East-west distance in longitude between adjacent samples (postings) in the raster, specified as a positive numeric scalar. The value is always positive, and is the constant throughout the raster.

Example: 2.5

Data Types: double

RasterExtentInLatitude — Latitude extent ("height") of the quadrangle covered by the raster

1 (default) | positive numeric scalar

This property is read-only.

Latitude extent ("height") of the quadrangle covered by the raster, specified as a positive numeric scalar.

Data Types: double

RasterExtentInLongitude — Longitude extent ("width") of the quadrangle covered by the raster

1 (default) | positive numeric scalar

This property is read-only.

Longitude extent ("width") of the quadrangle covered by the raster, specified as a positive numeric scalar.

Data Types: double

XIntrinsicLimits — Raster limits in intrinsic x coordinates

[1 2] (default) | two-element row vector of positive integers

This property is read-only.

Raster limits in intrinsic x coordinates, specified as a two-element row vector of positive integers, [xMin xMax]. For an *m*-by-*n* raster, XIntrinsicLimits equals [1 *m*], because the RasterInterpretation is 'postings'.

Data Types: double

YIntrinsicLimits — Raster limits in intrinsic y coordinates

[1 2] (default) | two-element row vector of positive integers

This property is read-only.

Raster limits in intrinsic y coordinates, specified as a two-element row vector of positive integers, [yMin yMax]. For an *m*-by-*n* raster, YIntrinsicLimits equals [1 *m*], because the RasterInterpretation is 'postings'.

Data Types: double

CoordinateSystemType — Type of coordinate system to which the image or raster is referenced

'geographic' (default) | two-element row vector of positive integers

This property is read-only.

Type of coordinate system to which the image or raster is referenced, specified as 'geographic'.

Data Types: char

Object Functions

| | |
|-----------------------|---|
| contains | Determine if geographic or map raster contains points |
| geographicToDiscrete | Transform geographic to discrete coordinates |
| geographicToIntrinsic | Transform geographic to intrinsic coordinates |
| intrinsicToGeographic | Transform intrinsic to geographic coordinates |
| intrinsicXToLongitude | Convert from intrinsic x to longitude coordinates |

| | |
|------------------------------------|--|
| <code>intrinsicYToLatitude</code> | Convert from intrinsic y to latitude coordinates |
| <code>latitudeToIntrinsicY</code> | Convert from latitude to intrinsic y coordinates |
| <code>longitudeToIntrinsicX</code> | Convert from longitude to intrinsic x coordinates |
| <code>sizesMatch</code> | Determine if geographic or map raster object and image or raster are size-compatible |
| <code>worldFileMatrix</code> | Return world file parameters for transformation |

Definitions

Intrinsic Coordinate System

A 2-D Cartesian system with its x -axis running parallel to the rows of a raster or image and its y -axis running parallel to the columns. x increases by 1 from column to column, and y increases by 1 from row to row.

Mapping Toolbox and Image Processing Toolbox use the convention for the location of the origin relative to the raster cells or sampling points such that, at a sample location or at the center of a cell, x has an integer value equal to the column index. Likewise, at a sample location or at the center of a cell, y has an integer value equal to the row index. For details, see Image Coordinate Systems (Image Processing Toolbox).

See Also

Functions

`georasterref` | `georefcells`

Objects

`GeographicCellsReference` | `MapCellsReference` | `MapPostingsReference`

Introduced in R2013b

geographicToDiscrete

Package: map.rasterref

Transform geographic to discrete coordinates

Syntax

```
[I,J] = geographicToDiscrete(R,lat,lon)
```

Description

`[I,J] = geographicToDiscrete(R,lat,lon)` returns the indices corresponding to geographic coordinates `lat` and `lon` in geographic raster `R`. If `R.RasterInterpretation` is:

- `'cells'`, then `I` and `J` are the row and column subscripts of the raster cells (or image pixels)
- `'postings'`, then `I` and `J` refer to the nearest sample point (posting)

Input Arguments

R — Geographic raster

GeographicCellsReference or GeographicPostingsReference object

Geographic raster, specified as a GeographicCellsReference or GeographicPostingsReference object.

lat — Latitude coordinates

numeric array

Latitude coordinates, specified as a numeric array.

Data Types: `single` | `double`

lon — Longitude coordinates

numeric array

Longitude coordinates, specified as a numeric array. lon is the same size as lat.

Data Types: single | double

Output Arguments

I — Longitude indices

array of integers

Longitude indices, returned as an array of integers. I is the same size as lat.

For an m -by- n raster, $1 \leq I \leq m$, except for points (lat(k), lat(k)) that fall outside the bounds of the raster as defined by the function contains. In this case I(k) and J(k) are NaN.

Data Types: double

J — Latitude indices

array of integers

Latitude indices, returned as an array of integers. J is the same size as lat.

For an m -by- n raster, $1 \leq J \leq n$ except for points (lat(k), lat(k)) that fall outside the bounds of the raster as defined by the function contains. In this case I(k) and J(k) are NaN.

Data Types: double

See Also

contains | geographicToIntrinsic | latitudeToIntrinsicY |
longitudeToIntrinsicX | worldToDiscrete

Introduced in R2013b

geographicToIntrinsic

Package: map.rasterref

Transform geographic to intrinsic coordinates

Syntax

```
[xIntrinsic,yIntrinsic] = geographicToIntrinsic(R,lat,lon)
```

Description

`[xIntrinsic,yIntrinsic] = geographicToIntrinsic(R,lat,lon)` returns the intrinsic coordinates corresponding to geographic coordinates `lat` and `lon` in geographic raster `R`.

Input Arguments

R — Geographic raster

GeographicCellsReference or GeographicPostingsReference object

Geographic raster, specified as a GeographicCellsReference or GeographicPostingsReference object.

lat — Latitude coordinates

numeric array

Latitude coordinates, specified as a numeric array. Valid values of `lat` are in the range `[-90, 90]` degrees or are `NaN`. `lat` coordinates can be outside the bounds of the raster `R`.

Data Types: `single` | `double`

lon — Longitude coordinates

numeric array

Longitude coordinates, specified as a numeric array. `lon` is the same size as `lat`. `lon` coordinates can be outside the bounds of the raster `R`.

Data Types: `single` | `double`

Output Arguments

xIntrinsic — x-coordinates in intrinsic coordinate system

numeric array

x-coordinates in intrinsic coordinate system, returned as a numeric array. `xIntrinsic` is the same size as `lat`.

When `lon(k)` is outside the bounds of raster `R`, `xIntrinsic(k)` is extrapolated in the intrinsic coordinate system.

Data Types: `double`

yIntrinsic — y-coordinates in intrinsic coordinate system

numeric array

y-coordinates in intrinsic coordinate system, returned as a numeric array. `yIntrinsic` is the same size as `lat`.

When `lat(k)` is valid and outside the bounds of raster `R`, `yIntrinsic(k)` is extrapolated in the intrinsic coordinate system.

Data Types: `double`

See Also

`geographicToDiscrete` | `intrinsicToGeographic` | `latitudeToIntrinsicY` | `longitudeToIntrinsicX` | `worldToIntrinsic`

Introduced in R2013b

geointerp

Geographic raster interpolation

Syntax

```
Vq = geointerp(V,R,latq,longq)
Vq = geointerp( ____,method)
```

Description

`Vq = geointerp(V,R,latq,longq)` interpolates the geographically referenced raster `V`, using bilinear interpolation. The function returns a value in `Vq` for each of the query points in arrays `latq` and `longq`. `R` is a geographic raster reference object that specifies the location and extent of data in `V`.

`Vq = geointerp(____,method)` specifies alternate interpolation methods.

Examples

Interpolate Values at Specific Latitudes and Longitudes

Load a georeferenced raster grid.

```
load topo
```

Create a raster reference object associated with the `topo` raster grid.

```
R = georefcells(topolatlim,topolonlim,size(topo))
```

```
R =
  GeographicCellsReference with properties:
```

```
    LatitudeLimits: [-90 90]
    LongitudeLimits: [0 360]
    RasterSize: [180 360]
```

```

RasterInterpretation: 'cells'
  ColumnsStartFrom: 'south'
  RowsStartFrom: 'west'
  CellExtentInLatitude: 1
  CellExtentInLongitude: 1
  RasterExtentInLatitude: 180
  RasterExtentInLongitude: 360
  XIntrinsicLimits: [0.5 360.5]
  YIntrinsicLimits: [0.5 180.5]
  CoordinateSystemType: 'geographic'
  AngleUnit: 'degree'

```

Define the points you want to interpolate using latitude and longitude.

```

mylats = [-40 -20 20 40];
mylons = [ 42 54 38 62];

```

Interpolate the values at the defined points.

```
Vinterpolated = geointerp(topo,R,mylats,mylons)
```

```

Vinterpolated = 1×4
103 ×

```

```

-2.8327   -4.3855   -0.7125    0.1700

```

Input Arguments

V — Georeferenced raster grid

numeric or logical array

Georeferenced raster grid, specified as numeric or logical array.

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64 | logical

R — Geographic raster

GeographicCellsReference or GeographicPostingsReference object

Geographic raster, specified as a `GeographicCellsReference` or `GeographicPostingsReference` object.

To convert a referencing matrix to a geographic raster reference object, use `refmatToGeoRasterReference`. To convert a referencing vector to a geographic raster reference object, use `refvecToGeoRasterReference`.

latq — Latitude of query point coordinates

numeric array

Latitude of query point coordinates, specified as a numeric array.

Data Types: `single` | `double`

long — Longitude of query point coordinates,

numeric array

Longitude of query point coordinates, specified as a numeric array.

Data Types: `single` | `double`

method — Interpolation methods

`'linear'` (default) | `'nearest'` | `'cubic'` | `'spline'`

Interpolation methods, specified as one of the following values.

| Method | Description |
|------------------------|--------------------------------|
| <code>'nearest'</code> | Nearest neighbor interpolation |
| <code>'linear'</code> | Bilinear interpolation |
| <code>'cubic'</code> | Bicubic interpolation |
| <code>'spline'</code> | Spline interpolation |

Data Types: `char` | `string`

Output Arguments

Vq — Interpolated values

numeric array

Interpolated values, returned as a numeric array.

See Also

`griddedInterpolant` | `interp2` | `mapinterp`

Introduced in R2017a

geoloc2grid

Convert geolocated data array to regular data grid

Syntax

```
[Z, refvec] = geoloc2grid(lat, lon, A, cellsize)
```

Description

`[Z, refvec] = geoloc2grid(lat, lon, A, cellsize)` converts the geolocated data array `A`, given geolocation points in `lat` and `lon`, to produce a regular data grid, `Z`, and the corresponding three-element referencing vector `refvec`. `cellsize` is a scalar that specifies the width and height of data cells in the regular data grid, using the same angular units as `lat` and `lon`. Data cells in `Z` falling outside the area covered by `A` are set to `NaN`.

Examples

```
% Load the geolocated data array 'map1'
% and grid it to 1/2-degree cells.
load mapmtx
cellsize = 0.5;
[Z, refvec] = geoloc2grid(lt1, lg1, map1, cellsize);

% Create a figure
f = figure;
[cmap, clim] = demcmap(map1);
set(f, 'Colormap', cmap, 'Color', 'w')

% Define map limits
latlim = [-35 70];
lonlim = [0 100];

% Display 'map1' as a geolocated data array in subplot 1
subplot(1,2,1)
ax = axesm('mercator', 'MapLatLimit', latlim, ...
```




```

    'MapLonLimit',lonlim,'Grid','on',...
    'MeridianLabel','on','ParallelLabel','on');
set(ax,'Visible','off')
geoshow(lt1, lg1, map1, 'DisplayType', 'texturemap');

% Display 'Z' as a regular data grid in subplot 2
subplot(1,2,2)
ax = axesm('mercator','MapLatLimit',latlim,...
    'MapLonLimit',lonlim,'Grid','on',...
    'MeridianLabel','on','ParallelLabel','on');
set(ax,'Visible','off')
geoshow(Z, refvec, 'DisplayType', 'texturemap');

```



Tips

geoloc2grid provides an easy-to-use alternative to gridding geolocated data arrays with `imbedm`. There is no need to preallocate the output map; there are no data gaps in the output (even if `cellsize` is chosen to be very small), and the output map is smoother.

Introduced before R2006a

geopeaks

Generate synthetic data set on sphere

Syntax

```
Z = geopeaks(lat, lon)
Z = geopeaks(R)
Z = geopeaks( ____, spheroid)
```

Description

`Z = geopeaks(lat, lon)` evaluates a "peaks-like" function at specific latitudes and longitudes on the surface of a sphere, returning the synthetic data set `Z`. The function is continuous and smooth at all points, including the poles. Reminiscent of the MATLAB `peaks` function, `geopeaks` undulates gently between values of `-10` and `8`, with about a half dozen local extrema.

`Z = geopeaks(R)` evaluates the `geopeaks` function at cell centers or sample posting points defined by a geographic raster reference object, `R`.

`Z = geopeaks(____, spheroid)` evaluates the function on a specific spheroid. The choice of spheroid makes very little difference; this option exists mainly to support formal testing.

Examples

Generate Profile Along Meridian

Define latitude and longitude values along meridian that includes Paris, France.


```
lon = dms2degrees([2 21 3]);
lat = -90:0.5:90;
```

Generate a data set, specifying a spheroid.

```
z = geopeaks(lat, lon, wgs84Ellipsoid);
```

Display the profile.

```
figure  
plot(lat,z)  
xlabel('Latitude')
```



Generate Global Raster and Display Results on World Map

Create a raster reference object for a 181-by-361 grid of postings.

```
latlim = [-90 90];
lonlim = [-180 180];
sampleSpacing = 1;
R = georefpostings(latlim,lonlim,sampleSpacing,sampleSpacing)
```

```
R =
  GeographicPostingsReference with properties:
```


```
    LatitudeLimits: [-90 90]
    LongitudeLimits: [-180 180]
    RasterSize: [181 361]
    RasterInterpretation: 'postings'
    ColumnsStartFrom: 'south'
    RowsStartFrom: 'west'
    SampleSpacingInLatitude: 1
    SampleSpacingInLongitude: 1
    RasterExtentInLatitude: 180
    RasterExtentInLongitude: 360
    XIntrinsicLimits: [1 361]
    YIntrinsicLimits: [1 181]
    CoordinateSystemType: 'geographic'
    AngleUnit: 'degree'
```

Generate a data set.

```
Z = geopeaks(R);
```

Display the resultant data set on a map.

```
figure
worldmap world
geoshow(Z,R,'DisplayType','surface','CData',Z,'ZData',zeros(size(Z)))
load coastlines
geoshow(coastlat,coastlon,'Color','k')
colorbar
```



Input Arguments

lat — Geodetic latitude of one or more points

scalar, vector, or matrix

Geodetic latitude of one or more points, specified as a scalar value, vector, or matrix. Values must be in degrees.

The `lat` input argument must match the `lon` input argument in size unless either value is scalar (in which case it will expand in size to match the other), or `lat` is a column vector and `lon` is a row vector (they will expand to form a plaid latitude-longitude mesh).

Example: `lat = -90:0.5:90`

Data Types: `single` | `double`

lon — Geodetic longitude of one or more points

scalar, vector, or matrix

Geodetic longitude of one or more points, specified as a scalar value, vector, or matrix. Values must be in degrees.

The `lon` input argument must match the `lat` input argument in size unless either value is scalar (in which case it will expand in size to match the other), or `lon` is a column vector and `lat` is a row vector (they will expand to form a plaid latitude-longitude mesh).

Example: `lon = -180:0.5:180`

Data Types: `single` | `double`

R — Geographic raster

`GeographicCellsReference` or `GeographicPostingsReference` object

Geographic raster, specified as a `GeographicCellsReference` or `GeographicPostingsReference` object. The geographic raster stores the latitude and longitude of points.

Example: `R = georefcells([0 80], [-140 60], 0.25, 0.25)`

spheroid — Reference spheroid

`referenceEllipsoid` | `oblateSpheroid` | `referenceSphere`

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object.

Example: `spheroid = referenceEllipsoid('GRS80')`

Output Arguments

Z — Synthetic data set

scalar value, vector, or matrix

Synthetic data set, returned as a scalar value, vector, or matrix of class `single` or `double`, depending on the class of the input. The function is evaluated at each element of

lat and lon (following expansion as noted above), or at each cell center or posting point defined by R.

See Also

peaks

Introduced in R2015b

geopoint

Geographic point vector

Description

A geopoint vector is a container object that holds geographic point coordinates and attributes. The points are coupled, such that the size of the latitude and longitude coordinate arrays are always equal and match the size of any dynamically added attribute arrays. Each entry of a coordinate pair and associated attributes, if any, represents a discrete element in the geopoint vector.

Creation

Syntax

```
p = geopoint()  
p = geopoint(latitude,longitude)  
p = geopoint(latitude,longitude,Name,Value)  
p = geopoint(structArray)  
p = geopoint(latitude,longitude,structArray)
```

Description

`p = geopoint()` constructs an empty geopoint vector with these default property settings:

```
p =
```

```
0x1 geopoint vector with properties:
```

```
Collection properties:
```

```
    Geometry: 'point'
```

```
    Metadata: [1x1 struct]
```

```
Feature properties:
```



```
Latitude: []  
Longitude: []
```

`p = geopoint(latitude, longitude)` sets the `Latitude` and `Longitude` properties of geopoint vector `p`

`p = geopoint(latitude, longitude, Name, Value)` sets the `Latitude` and `Longitude` properties, then adds dynamic properties to the geopoint vector using `Name, Value` argument pairs. You can specify several name-value pair arguments in any order as `Name1, Value1, . . . , NameN, ValueN`.

`p = geopoint(structArray)` constructs a new geopoint vector from the fields of the structure, `structArray`.

- If `structArray` contains the field `Lat`, and does not contain a field `Latitude`, then the `Lat` values are assigned to the `Latitude` property. Similar behavior occurs when `structArray` contains the field `Lon`, and does not contain the field `Longitude`.
- If `structArray` contains both `Lat` and `Latitude` fields, then both field values are assigned to `p`. Similar behavior occurs for `Lon` and `Longitude` fields when both are present in `structArray`
- Other fields of `structArray` are assigned to `p` and become dynamic properties. Field values in `structArray` that are not numeric data types, string scalars, string arrays, character vectors, or cell arrays of numeric data types or character vectors are ignored.

`p = geopoint(latitude, longitude, structArray)` sets the `Latitude` and `Longitude` properties, and sets dynamic properties from the field values of the structure, `structArray`.

- If `structArray` contains the fields `Lat`, `Latitude`, `Lon`, or `Longitude`, then those field values are ignored.

Properties

Each element in a geopoint vector is considered a feature. For more about the property types in `geopoint`, see “Collection Properties” on page 1-505 and “Feature Properties” on page 1-505.

Dynamic properties are new features that are added to a geopoint vector and that apply to each individual feature in the geopoint vector. You can attach new dynamic Feature

properties to the object during construction with a `Name, Value` pair or after construction using dot (`.`) notation. This is similar to adding dynamic fields to a structure. For an example of adding dynamic Feature properties, see “Construct Geopoint Vector Using Name-Value Pairs” on page 1-491.

Geometry — Type of geometry

`'point'`

Type of geometry, specified as `'point'`. For geopoint, `Geometry` is always `'point'`.

Data Types: `char` | `string`

Latitude — Latitude coordinates

numeric row or column vector

Latitude coordinates, specified as a numeric row or column vector.

Data Types: `double` | `single`

Longitude — Longitude coordinates

numeric row or column vector

Longitude coordinates, specified as a numeric row or column vector.

Data Types: `double` | `single`

Metadata — Information for the entire set of geopoint vector elements

scalar structure

Information for the entire set of geopoint vector elements, specified as a scalar structure. You can add any data type to the structure.

- If `Metadata` is provided as a dynamic property `Name` in the constructor, and the corresponding `Value` is a scalar structure, then `Value` is copied to the `Metadata` property. Otherwise, an error is issued.
- If a `Metadata` field is provided by `structArray`, and both `Metadata` and `structArray` are scalar structures, then the `Metadata` field value is copied to the `Metadata` property value. If `structArray` is a scalar but the `Metadata` field is not a structure, then an error is issued. If `structArray` is not scalar, then the `Metadata` field is ignored.

Data Types: `struct`

Object Functions

| | |
|------------|---|
| append | Append features to geographic or planar vector |
| cat | Concatenate geographic or planar vector |
| disp | Display geographic or planar vector |
| fieldnames | Return dynamic property names of geographic or planar vector |
| isempty | Determine if geographic or planar vector is empty |
| isfield | Determine if dynamic property exists in geographic or planar vector |
| isprop | Determine if property exists in geographic or planar vector |
| length | Return number of elements in geographic or planar vector |
| properties | Return property names of geographic or planar vector |
| rmfield | Remove dynamic property from geographic or planar vector |
| rmprop | Remove property from geographic or planar vector |
| size | Return size of geographic or planar vector |
| struct | Convert geographic or planar vector to scalar structure |
| vertcat | Vertically concatenate geographic or planar vectors |

Examples

Construct Geopoint Vector Using Latitude and Longitude Coordinates

This example shows how to create a geopoint vector specifying latitude and longitude coordinates. The example then adds a property to the object dynamically.

Construct a geopoint vector from latitude and longitude values.

```
lat = [51.519 42.356];
lon = [-.13 -71.101];
p = geopoint(lat,lon)

p =
  2x1 geopoint vector with properties:

  Collection properties:
    Geometry: 'point'
    Metadata: [1x1 struct]
  Feature properties:
    Latitude: [51.5190 42.3560]
    Longitude: [-0.1300 -71.1010]
```

Add a property to the object dynamically.

```
p.Name = {'London', 'Boston'}
```

```
p =  
2x1 geopoint vector with properties:
```

```
Collection properties:
```

```
Geometry: 'point'
```

```
Metadata: [1x1 struct]
```

```
Feature properties:
```

```
Latitude: [51.5190 42.3560]
```

```
Longitude: [-0.1300 -71.1010]
```

```
Name: {'London' 'Boston'}
```

Construct Geopoint Vector from File

Load coast line data from a MAT-file.

```
load coastlines
```

Construct a geopoint vector from the coastline latitude and longitude file.


```
p = geopoint(coastlat, coastlon);
```

Display the points on a world map.

```
figure
```

```
worldmap world
```

```
geoshow(p.Latitude, p.Longitude)
```



Construct Geopoint Vector Using Name-Value Pairs

Create a geopoint vector, specifying Latitude, Longitude, and Temperature, where Temperature is part of a Name-Value pair.

```
point = geopoint(42, -72, 'Temperature', 89)
```

```
point =
```

```
1x1 geopoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: 42
  Longitude: -72
  Temperature: 89
```

Construct a geopoint object specifying names.

```
p = geopoint([51.519 48.871], [-.13 2.4131], ...
  'Name', {"London", "Paris"})
```

p =

2x1 geopoint vector with properties:

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: [51.5190 48.8710]
  Longitude: [-0.1300 2.4131]
  Name: {'London' 'Paris'}
```

Construct Geopoint Vector From a Structure Array

Read shape data into a geostruct (a structure array containing Lat and Lon fields).

```
S = shaperead('worldcities', 'UseGeoCoords', true)
```

S =

318x1 struct array with fields:

```
  Geometry
  Lon
  Lat
  Name
```

Create a geopoint vector specifying the geostruct.

```
p = geopoint(S)
```

```
p =
318x1 geopoint vector with properties:

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: [1x318 double]
  Longitude: [1x318 double]
  Name: {1x318 cell}
```

Add a `Filename` field to the `Metadata` structure. The `Metadata` property pertains to all elements of a `geopoint` vector.

```
p.Metadata.Filename = 'worldcities.shp';
m = p.Metadata

ans =

    Filename: 'worldcities.shp'
```

Construct a Geopoint Vector Using Numeric Arrays and a Structure Array

Create a structure array.

```
[structArray, A] = shaperead('worldcities', 'UseGeoCoords', true)

structArray =

318x1 struct array with fields:
  Geometry
  Lon
  Lat
```

```
A =
```

```
318x1 struct array with fields:
  Name
```

Use the numeric arrays and the structure containing the list of names to construct a `geopoint` vector.

```
p = geopoint([structArray.Lat], [structArray.Lon], A)
```

```
p =  
  
318x1 geopoint vector with properties:  
  
Collection properties:  
    Geometry: 'point'  
    Metadata: [1x1 struct]  
Feature properties:  
    Latitude: [1x318 double]  
    Longitude: [1x318 double]  
    Name: {1x318 cell}
```

Add Coordinate and Dynamic Properties

Generate an empty geopoint vector using the default constructor, then populate the geopoint vector using dot notation with properties from data fields in structure structArray.

```
structArray = shaperead('worldcities', 'UseGeoCoords', true);  
p = geopoint();  
p.Latitude = [structArray.Lat];  
p.Longitude = [structArray.Lon];  
p.Name = structArray.Name;  
p
```

```
p =  
  
318x1 geopoint vector with properties:  
  
Collection properties:  
    Geometry: 'point'  
    Metadata: [1x1 struct]  
Feature properties:  
    Latitude: [1x318 double]  
    Longitude: [1x318 double]  
    Name: {1x318 cell}
```

Add New Values to Existing geopoint Vector

This example shows how to add new values to an existing geopoint vector. The example appends data about Paderborn Germany to the geopoint vector of data about world cities.

Read world cities data using the `shaperead` command. `shaperead` returns a structure array.

```
structArray = shaperead('worldcities.shp', 'UseGeoCoords', true);
```

Create a geopoint vector from the structure array. Display the last of the 318 elements in the vector.

```
p = geopoint(structArray);  
p(end)
```

```
ans =  
1x1 geopoint vector with properties:
```

```
Collection properties:  
  Geometry: 'point'  
  Metadata: [1x1 struct]  
Feature properties:  
  Latitude: 34.8519  
  Longitude: 113.8061  
  Name: 'Zhengzhou'
```

Add the Paderborn data to the end of the geopoint vector. Display the last of the existing elements and the new element.

```
lat = 51.715254;  
lon = 8.75213;  
p = append(p, lat, lon, 'Name', 'Paderborn');  
p(end-1:end)
```

```
ans =  
2x1 geopoint vector with properties:
```

```
Collection properties:  
  Geometry: 'point'  
  Metadata: [1x1 struct]  
Feature properties:  
  Latitude: [34.8519 51.7153]  
  Longitude: [113.8061 8.7521]  
  Name: {'Zhengzhou' 'Paderborn'}
```

Another way to add a point at the end of a vector is to use linear indexing. For example, add data about Arlington, Massachusetts to the end of the world cities vector. Notice how,

after the initial assignment statement appends a value to the Latitude property vector, using `end+1`, all other property vectors automatically expand by one element. Display the last of the existing elements and the new element.

```
p(end+1).Latitude = 42.417060

p =
  320x1 geopoint vector with properties:

  Collection properties:
    Geometry: 'point'
    Metadata: [1x1 struct]
  Feature properties:
    Latitude: [1x320 double]
    Longitude: [1x320 double]
    Name: {1x320 cell}

p(end).Longitude = -71.170200;
p(end).Name = 'Arlington';
p(end-1:end)

ans =
  2x1 geopoint vector with properties:

  Collection properties:
    Geometry: 'point'
    Metadata: [1x1 struct]
  Feature properties:
    Latitude: [51.7153 42.4171]
    Longitude: [8.7521 -71.1702]
    Name: {'Paderborn' 'Arlington'}
```

Manipulate a Geopoint Vector

Construct a geopoint vector containing two features and then add two dynamic properties.

```
lat = [51.519 48.871];
lon = [-.13 2.4131];
p = geopoint(lat, lon);
```

```
p.Name = {'London', 'Paris'}; % Add character feature dynamic property
p.ID = [1 2] % Add numeric feature dynamic property
```

```
p =
```

```
2x1 geopoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: [51.5190 48.8710]
  Longitude: [-0.1300 2.4131]
  Name: {'London' 'Paris'}
  ID: [1 2]
```

Add the coordinates for a third feature.

```
p(3).Latitude = 45.472;
p(3).Longitude = 9.184
```

```
p =
```

```
3x1 geopoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: [51.5190 48.8710 45.4720]
  Longitude: [-0.1300 2.4131 9.1840]
  Name: {'London' 'Paris' ''}
  ID: [1 2 0]
```

Note that lengths of all feature properties are synchronized with default values.

Set the values for the ID feature dynamic property with more values than contained in Latitude or Longitude.

```
p.ID = 1:4
```

```
p =
```

```
4x1 geopoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: [51.5190 48.8710 45.4720 0]
  Longitude: [-0.1300 2.4131 9.1840 0]
  Name: {'London' 'Paris' '' ''}
  ID: [1 2 3 4]
```

Note that all feature properties are expanded to match in size.

Set the values for the ID feature dynamic property with fewer values than contained in the `Latitude` or `Longitude` properties.

```
p.ID = 1:2
```

```
p =
```

```
4x1 geopoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: [51.5190 48.8710 45.4720 0]
  Longitude: [-0.1300 2.4131 9.1840 0]
  Name: {'London' 'Paris' '' ''}
  ID: [1 2 0 0]
```

The ID property values expand to match the length of the `Latitude` and `Longitude` property values.

Set the value of either coordinate property (`Latitude` or `Longitude`) with fewer values.

```
p.Latitude = [51.519 48.871]
```

```
p =
```

```
2x1 geopoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
```

```

Latitude: [51.5190 48.8710]
Longitude: [-0.1300 2.4131]
Name: {'London' 'Paris'}
ID: [1 2]

```

All properties shrink to match in size.

Remove the ID property by setting its value to [].

```
p.ID = []
```

```
p =
```

```
2x1 geopoint vector with properties:
```

```

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: [51.5190 48.8710]
  Longitude: [-0.1300 2.4131]
  Name: {'London' 'Paris'}

```

Remove all dynamic properties and set the object to empty by setting a coordinate property value to [].

```
p.Latitude = []
```

```
p =
```

```
0x1 geopoint vector with properties:
```

```

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: []
  Longitude: []

```

Sort Dynamic Properties and Extract Subsets

Read data from shapefile. Initially the field names of the class are in random order.

```
structArray = shaperead('tsunamis', 'UseGeoCoords', true); % Field names in random order
p = geopoint(structArray)
```

```
p =
```

```
162x1 geopoint vector with properties:
```

```
Collection properties:
```

```
    Geometry: 'point'
```

```
    Metadata: [1x1 struct]
```

```
Feature properties:
```

```
    Latitude: [1x162 double]
```

```
    Longitude: [1x162 double]
```

```
        Year: [1x162 double]
```

```
        Month: [1x162 double]
```

```
        Day: [1x162 double]
```

```
        Hour: [1x162 double]
```

```
        Minute: [1x162 double]
```

```
        Second: [1x162 double]
```

```
    Val_Code: [1x162 double]
```

```
    Validity: {1x162 cell}
```

```
    Cause_Code: [1x162 double]
```

```
        Cause: {1x162 cell}
```

```
        Eq_Mag: [1x162 double]
```

```
        Country: {1x162 cell}
```

```
        Location: {1x162 cell}
```

```
    Max_Height: [1x162 double]
```

```
    Iida_Mag: [1x162 double]
```

```
    Intensity: [1x162 double]
```

```
    Num_Deaths: [1x162 double]
```

```
    Desc_Deaths: [1x162 double]
```

Using the method `fieldnames` and typical MATLAB vector notation, the field names in the geopoint vector are alphabetically sorted.

```
p = p(:, sort(fieldnames(p)))
```

```
p =
```

```
162x1 geopoint vector with properties:
```

```
Collection properties:
```

```
    Geometry: 'point'
```

```
    Metadata: [1x1 struct]
```

```
Feature properties:
```

```

Latitude: [1x162 double]
Longitude: [1x162 double]
Cause: {1x162 cell}
Cause_Code: [1x162 double]
Country: {1x162 cell}
Day: [1x162 double]
Desc_Deaths: [1x162 double]
Eq_Mag: [1x162 double]
Hour: [1x162 double]
Iida_Mag: [1x162 double]
Intensity: [1x162 double]
Location: {1x162 cell}
Max_Height: [1x162 double]
Minute: [1x162 double]
Month: [1x162 double]
Num_Deaths: [1x162 double]
Second: [1x162 double]
Val_Code: [1x162 double]
Validity: {1x162 cell}
Year: [1x162 double]

```

Using typical MATLAB vector notation, extract a subset of data from the base geopoint vector into a geopoint vector albeit smaller in size.

```
subp = p(20:40,{'Location','Country','Year'}) % get subset of data
```

```
subp =
```

```
21x1 geopoint vector with properties:
```

```

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: [1x21 double]
  Longitude: [1x21 double]
  Location: {1x21 cell}
  Country: {1x21 cell}
  Year: [1x21 double]

```

Note that the coordinate properties `Latitude` and `Longitude`, and the Collection properties, are retained in this subset of geopoint vectors.

Set, Get, and Remove Dynamic Property Values

To set property values, use the () operator, or assign array values to corresponding fields, or use dot ' .' notation (object.property) to assign new property values.

```
pts = geoint();
pts.Latitude = [42 44 45];
pts.Longitude = [-72 -72.1 -71];
pts
```

```
pts =
```

```
3x1 geoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: [42 44 45]
  Longitude: [-72 -72.1000 -71]
```

Use () to assign values to fields.

```
pts(3).Latitude = 45.5;
pts
```

```
pts =
```

```
3x1 geoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: [42 44 45.5000]
  Longitude: [-72 -72.1000 -71]
```

Use dot notation to create new dynamic properties

```
pts.Name = {'point1', 'point2', 'point3'}
```

```
pts =
```

```
3x1 geoint vector with properties:
```



```

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: [42 44 45.5000]
  Longitude: [-72 -72.1000 -71]
  Name: {'point1' 'point2' 'point3'}

```

Get property values

```
pts.Name
```

```
ans =
```

```
'point1' 'point2' 'point3'
```

Remove dynamic properties. To delete or remove dynamic properties, set them to [] or set the Latitude or Longitude property to [].

```
pts.Temperature = 1:3
```

```
pts =
```

```
3x1 geopoint vector with properties:
```

```

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: [42 44 45.5000]
  Longitude: [-72 -72.1000 -71]
  Name: {'point1' 'point2' 'point3'}
  Temperature: [1 2 3]

```

By setting the Temperature property to [], this dynamic property is deleted.

```
pts.Temperature = []
```

```
pts =
```

```
3x1 geopoint vector with properties:
```

```

Collection properties:
  Geometry: 'point'

```

```
Metadata: [1x1 struct]
Feature properties:
  Latitude: [42 44 45.5000]
  Longitude: [-72 -72.1000 -71]
  Name: {'point1' 'point2' 'point3'}
```

To clear all fields in the `geopoint` vector, set the `Latitude` or `Longitude` property to `[]`.

```
pts.Latitude = []
```

```
pts =
```

```
0x1 geopoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: []
  Longitude: []
```

Modify geopoint Object and Its Metadata

If you typically store latitude and longitude coordinates in an N -by-2 or 2-by- M array, you can assign these numeric values to a `geopoint` vector. If the coordinates are N -by-2, the first column is assigned to the `Latitude` property and the second column to the `Longitude` property. If the coordinates are 2-by- M , then the first row is assigned to the `Latitude` property and the second row to the `Longitude` property.

```
load coastlines;
ltn = [coastlat coastlon];           % 9865x2 array
pts = geopoint;                     % null constructor
pts(1:numel(coastlat)) = ltn;       % assign array
pts.Metadata.Name = 'coastline';
pts
```

```
pts =
9865x1 geopoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
```

```
Feature properties:  
  Latitude: [1x9865 double]  
  Longitude: [1x9865 double]
```

```
pts.Metadata
```

```
ans = struct with fields:  
  Name: 'coastline'
```

Definitions

Collection Properties

Collection properties contain only one value per class instance. In contrast, the Feature property type has attribute values associated with each feature. `Geometry` and `Metadata` are the only two Collection properties.

Feature Properties

Feature properties contain one value (a scalar number, a scalar string, or a character vector) for each feature in a geopoint vector. They are suitable for properties such as name, owner, serial number, or age, that describe a given feature (an element of a geopoint vector) as a whole. The `Latitude` and `Longitude` coordinate properties are feature properties as there is one value for each element in the geopoint vector.

Feature properties can be added after construction using dot notation. This is similar to adding dynamic fields to a structure.

Tips

- If `Latitude`, `Longitude`, or a dynamic property is set with more values than features in the geopoint vector, then all other properties expand in size using 0 for numeric values and an empty character vector (' ') for cell values. See “Manipulate a Geopoint Vector” on page 1-496 for examples of these behaviors.

- If a dynamic property is set with fewer values than the number of features, then this dynamic property expands to match the size of the other properties by inserting a 0, if the value is numeric, or an empty character vector (' '), if the value is a cell array.
- If the `Latitude` or `Longitude` property of the geopoint vector is set with fewer values than contained in the object, then all other properties shrink in size.
- If either `Latitude` or `Longitude` are set to `[]`, then both coordinate properties are set to `[]` and all dynamic properties are removed.
- If a dynamic property is set to `[]`, then it is removed from the object.

See Also

Functions

`gpxread` | `shaperead`

Objects

`geoshape` | `mappoint` | `mapshape`

Introduced in R2012a

geoquadline

Geographic quadrangle bounding multi-part line

Syntax

```
[latlim,lonlim] = geoquadline(lat,lon)
```

Description

[latlim,lonlim] = geoquadline(lat,lon) returns the limits of the tightest possible geographic quadrangle that bounds a line connecting vertices with geographic coordinates specified by lat and lon.

Examples

Bounding Quadrangle for the Brahmaputra River

Read shape data and then create a bounding box around the line.

```
brahmaputra = shaperead('worldrivers.shp','Selector',{@(name) strcmp(name,'Brahmaputra')})
[latlim,lonlim] = geoquadline(brahmaputra.Lat, brahmaputra.Lon)
```

```
latlim =
```

```
    23.8285    30.3831
```

```
lonlim =
```

81.8971 95.4970

Input Arguments

lat — Latitudes along a line

vector

Latitudes along a line, specified as a vector representing an ordered sequences of vertices, in units of degrees. The line may be broken into multiple parts, delimited by values of **NaN**.

Data Types: `single` | `double`

lon — Longitudes along a line

vector

Longitudes along a line, specified as a vector representing an ordered sequences of vertices, in units of degrees. The line may be broken into multiple parts, delimited by values of **NaN**.

Data Types: `single` | `double`

Output Arguments

latlim — Latitude limits

1-by-2 vector

Latitude limits of a geographic quadrangle, returned as a 1-by-2 vector of the form `[southern_limit northern_limit]`, in units of degrees. The elements are in ascending order, and both lie in the closed interval `[-90 90]`.

lonlim — Longitude limits

1-by-2 vector

Longitude limits of a geographic quadrangle, returned as a 1-by-2 vector of the form `[western_limit eastern_limit]`, in units of degrees. The limits are wrapped to the interval `[-180 180]`. They are not necessarily in numerical ascending order.

See Also

`bufgeoquad` | `geoquadpt` | `ingeoquad` | `outlinegeoquad`

Introduced in R2012b

geoquadpt

Geographic quadrangle bounding scattered points

Syntax

```
[latlim,lonlim] = geoquadpt(lat,lon)
```

Description

`[latlim,lonlim] = geoquadpt(lat,lon)` returns the limits of the tightest possible geographic quadrangle that bounds a set of points with geographic coordinates `lat` and `lon`.

In most cases, `tf = ingeoquad(lat,lon,latlim,lonlim)` will return true, but `tf` may be false for points on the edges of the quadrangle, due to round off. `tf` will also be false for elements of `lat` that fall outside the interval `[-90 90]` and elements of `lon` that are not finite.

Examples

Bounding Quadrangle Including Tokyo and Honolulu

In this case the output quadrangle straddles the 180-degree meridian, hence the elements of `lonlim` are in descending numerical order, although they are ordered from west to east.

Read a set of points and then create a bounding box around the points.

```
cities = shaperead('worldcities.shp','Selector',{@(name) any(strcmp(name,{'Tokyo','Honolulu'}))}
[latlim,lonlim] = geoquadpt([cities.Lat],[cities.Lon])
```

```
latlim =
```

```
21.3178    35.7082
```



```
lonlim =  
    139.6401 -157.8291
```

Input Arguments

lat — Point latitudes

vector | matrix | N-D array

Point latitudes, specified as a vector, matrix, or N-D array, in units of degrees.

Data Types: `single` | `double`

lon — Point longitudes

vector | matrix | N-D array

Point longitudes, specified as a vector, matrix, or N-D array, in units of degrees.

Data Types: `single` | `double`

Output Arguments

latlim — Latitude limits

1-by-2 vector

Latitude limits of a geographic quadrangle, returned as a 1-by-2 vector of the form `[southern_limit northern_limit]`, in units of degrees. The elements are in ascending order, and both lie in the closed interval `[-90 90]`.

lonlim — Longitude limits

1-by-2 vector

Longitude limits of a geographic quadrangle, returned as a 1-by-2 vector of the form `[western_limit eastern_limit]`, in units of degrees. The limits are wrapped to the interval `[-180 180]`. They are not necessarily in numerical ascending order.

See Also

`bufgeoquad` | `geoquadline` | `ingeoquad` | `outlinegeoquad`

Introduced in R2012b

georasterref

Construct geographic raster reference object

Note Use the `georefcells` function or the `georefpostings` function instead, except when constructing a raster reference object from world file input.

Syntax

```
R = georasterref()  
R = georasterref(Name,Value)  
R = georasterref(W,rasterSize,rasterInterpretation)
```

Description

`R = georasterref()` constructs a geographic raster reference object with default property values.

`R = georasterref(Name,Value)` accepts a list of name-value pairs that are used to assign selected properties when initializing a geographic raster reference object.

`R = georasterref(W,rasterSize,rasterInterpretation)` constructs a geographic raster reference object with the specified raster size and interpretation properties, and with remaining properties defined by the world file matrix `W`. The `rasterInterpretation` input is optional, can equal either `'cells'` or `'postings'`, and has a default value of `'cells'`.

Input Arguments

W — World file matrix

2-by-3 numeric array

World file matrix, specified as a 2-by-3 numeric array. Each of the six elements in `W` matches one of the lines in a world file that defines the transformation in raster referencing object `R`.

Data Types: double

rasterSize — Number of rows and columns of the raster

two-element vector

Number of rows (*m*) and columns (*n*) of the raster or image associated with the referencing object, specified as a two-element vector [*m n*]. For convenience, you may assign a size vector having more than two elements to `RasterSize`. This flexibility enables assignments like `R.RasterSize = size(RGB)`, for example, where `RGB` is *m*-by-*n*-by-3. However, in such cases, only the first two elements of the size vector are actually stored. The higher (non-spatial) dimensions are ignored.

rasterInterpretation — Control to handle raster edges

'cells' (default) | 'postings'

Controls handling of raster edges. The `rasterInterpretation` input is optional, and can equal either 'cells' or 'postings'.

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1,Value1,...,NameN,ValueN`.

You can include any of the following properties, overriding their default values as needed. Alternatively, you may omit any or all properties when constructing your geographic raster reference object. Then, you can customize the result by resetting properties from this list one at a time. The exception is the `RasterInterpretation` property. To have a raster interpretation of 'postings' (rather than the default, 'cells'), the name-value pair '`RasterInterpretation`', 'postings' must be specified in your call to `georasterref`.

LatitudeLimits

Limits in latitude of the geographic quadrangle bounding the georeferenced raster. A two-element vector of the form:

```
[southern_limit northern_limit]
```

Default: [0.5 2.5]

LongitudeLimits

Limits in longitude of the geographic quadrangle bounding the georeferenced raster. A two-element vector of the form:

```
[western_limit eastern_limit]
```

Default: [0.5 2.5]

RasterSize

Two-element vector [m n] specifying the number of rows (m) and columns (n) of the raster or image associated with the referencing object. For convenience, you may assign a size vector having more than two elements to `RasterSize`. This flexibility enables assignments like `R.RasterSize = size(RGB)`, for example, where `RGB` is m -by- n -by-3. However, in such cases, only the first two elements of the size vector are actually stored. The higher (non-spatial) dimensions are ignored.

Default: [2 2]

RasterInterpretation

Controls handling of raster edges, specified as either 'cells' or 'postings'. If you want this property to have other than the default value, you must set it when you create the object. Once created, you cannot change the value of this property in a geographic raster reference object.

Default: 'cells'

ColumnsStartFrom

Edge from which column indexing starts, specified as either 'south' or 'north'.

Default: 'south'

RowsStartFrom

Edge from which row indexing starts, specified as either 'west' or 'east'.

Default: 'west'

Output Arguments

R — Geographic raster

GeographicCellsReference or GeographicPostingsReference object

Geographic raster, specified as a GeographicCellsReference or GeographicPostingsReference object.

Examples

Construct a referencing object for a global raster comprising a grid of 180-by-360 one-degree cells, with rows that start at longitude -180, and with the first cell located in the northwest corner.

```
R = georasterref('RasterSize', [180 360], ...  
    'RasterInterpretation', 'cells', 'ColumnsStartFrom', 'north', ...  
    'LatitudeLimits', [-90 90], 'LongitudeLimits', [-180 180])
```

Construct a referencing object for the DTED Level 0 file that includes Sagarmatha (Mount Everest). The DTED columns run from south to north and the first column runs along the western edge of the (one-degree-by-one-degree) quadrangle, consistent with the default values for 'ColumnsStartFrom' and 'RowsStartFrom'.

```
R = georasterref('LatitudeLimits', [27 28], 'LongitudeLimits', [86 87], ...  
    'RasterSize', [121 121], 'RasterInterpretation', 'postings')
```

Repeat the second example with a different strategy: Create an object by specifying only the RasterInterpretation value, then modify the object by resetting additional properties. (As noted above, the RasterInterpretation of an existing raster reference object cannot be changed.)

```
R = georasterref('RasterInterpretation', 'postings');  
R.RasterSize = [121 121];  
R.LatitudeLimits = [27 28];  
R.LongitudeLimits = [86 87];
```

Repeat the first example using a world file matrix as input.

```
W = [1    0   -179.5; ...  
     0   -1    89.5];  
rasterSize = [180 360];
```

```
rasterInterpretation = 'cells';  
R = georasterref(W, rasterSize, rasterInterpretation);
```

See Also

Functions

[georefcells](#) | [georefpostings](#) | [maprasterref](#) | [worldFileMatrix](#)

Objects

[GeographicCellsReference](#) | [GeographicPostingsReference](#)

Introduced in R2011a

georefpostings

Reference raster postings to geographic coordinates

Syntax

```
R = georefpostings()  
R = georefpostings(latlim, lonlim, rasterSize)  
R = georefpostings(latlim, lonlim, sampleSpacingInLatitude,  
sampleSpacingInLongitude)  
R = georefpostings(latlim, lonlim, ____, Name, Value)
```

Description

`R = georefpostings()` returns a default referencing object for a raster of regularly posted samples in geographic coordinates.

`R = georefpostings(latlim, lonlim, rasterSize)` constructs a referencing object for a raster spanning the specified limits in latitude and longitude, with the numbers of rows and columns specified by `rasterSize`.

`R = georefpostings(latlim, lonlim, sampleSpacingInLatitude, sampleSpacingInLongitude)` allows the geographic sample spacings to be set precisely. The geographic limits will be adjusted slightly, if necessary, to ensure an integer number of samples in each dimension.

`R = georefpostings(latlim, lonlim, ____, Name, Value)` allows the directions of the columns and rows to be specified via name-value pairs.

Examples

Construct Geographic Referencing Object for Global Raster

Define latitude and longitude limits and the dimensions of the raster.


```
latlim = [-90 90];
lonlim = [-180 180];
rasterSize = [181 361];
```

Create the referencing object specifying the raster size.

```
R = georefpostings(latlim,lonlim,rasterSize,'ColumnsStartFrom','north')
```

```
R =
  GeographicPostingsReference with properties:
    LatitudeLimits: [-90 90]
    LongitudeLimits: [-180 180]
    RasterSize: [181 361]
    RasterInterpretation: 'postings'
    ColumnsStartFrom: 'north'
    RowsStartFrom: 'west'
    SampleSpacingInLatitude: 1
    SampleSpacingInLongitude: 1
    RasterExtentInLatitude: 180
    RasterExtentInLongitude: 360
    XIntrinsicLimits: [1 361]
    YIntrinsicLimits: [1 181]
    CoordinateSystemType: 'geographic'
    AngleUnit: 'degree'
```

Obtain the same result by specifying the sample spacing.

```
spacing = 1;
```

```
R = georefpostings(latlim,lonlim,spacing,spacing,'ColumnsStartFrom','north')
```

```
R =
  GeographicPostingsReference with properties:
    LatitudeLimits: [-90 90]
    LongitudeLimits: [-180 180]
    RasterSize: [181 361]
    RasterInterpretation: 'postings'
    ColumnsStartFrom: 'north'
    RowsStartFrom: 'west'
    SampleSpacingInLatitude: 1
    SampleSpacingInLongitude: 1
```

```
RasterExtentInLatitude: 180
RasterExtentInLongitude: 360
  XIntrinsicLimits: [1 361]
  YIntrinsicLimits: [1 181]
CoordinateSystemType: 'geographic'
  AngleUnit: 'degree'
```

Input Arguments

latlim — Latitude limits in degrees

[0.5 2.5] (default) | 1-by-2 numeric vector

Latitude limits in degrees, specified as a 1-by-2 numeric vector. The number of rows in the resulting raster is specified by `rasterSize`.

Example: `latlim = [-90 90];`

Data Types: double

lonlim — Longitude limits in degrees

[0.5 2.5] (default) | 1-by-2 numeric vector

Longitude limits in degrees, specified as a 1-by-2 numeric vector. The number of columns in the resulting raster is specified by `rasterSize`.

Example: `lonlim = [-180 180];`

Data Types: double

rasterSize — Size of the raster

[2 2] (default) | 1-by-2 numeric vector

Size of the raster, specified as a 1-by-2 numeric vector.

Example: `rasterSize = [180 360];`

Data Types: double

sampleSpacingInLatitude — Vertical spacing of posting

1 (default) | numeric scalar

Vertical spacing of posting, specified as a numeric scalar.

Example: `spacing = 1.5`

Data Types: `double`

sampleSpacingInLongitude — Horizontal spacing of postings

1 (default) | numeric scalar

Horizontal spacing of postings, specified as a numeric scalar.

Example: `spacing = 1.5`

Data Types: `double`

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

Example: `R =`

```
georefpostings(latlim, lonlim, rasterSize, 'ColumnsStartFrom', 'north')
```

ColumnsStartFrom — Edge from which column indexing starts

'south' (default) | 'north'

Edge from which column indexing starts, specified as either 'north' or 'south'.

Example: `R =`

```
georefpostings(latlim, lonlim, rasterSize, 'ColumnsStartFrom', 'north')
```

Data Types: `char` | `string`

RowsStartFrom — Edge from which row indexing starts

'west' (default) | 'east'

Edge from which column indexing starts, specified as either 'east' or 'west'.

Example: `R =`

```
georefpostings(latlim, lonlim, rasterSize, 'RowsStartFrom', 'east')
```

Data Types: `char` | `string`

Output Arguments

R — Object that references raster postings to geographic coordinates

GeographicPostingsReference raster reference object

Object that references raster postings to geographic coordinates, returned as a GeographicPostingsReference raster reference object.

Tips

- To construct a geographic raster reference object from a world file matrix, use the `georasterref` function.

See Also

GeographicPostingsReference | `georefcells` | `maprefpostings`

Introduced in R2015b

georefcells

Reference raster cells to geographic coordinates

Syntax

```
R = georefcells()  
R = georefcells(latlim, lonlim, rasterSize)  
R = georefcells(latlim, lonlim, cellExtentInLatitude,  
cellExtentInLongitude)  
R = georefcells(latlim, lonlim, ____, Name, Value)
```

Description

`R = georefcells()` returns a default referencing object for a regular raster of cells in geographic coordinates.

`R = georefcells(latlim, lonlim, rasterSize)` constructs a referencing object for a raster of cells spanning the specified limits in latitude and longitude, with the numbers of rows and columns specified by `rasterSize`.

`R = georefcells(latlim, lonlim, cellExtentInLatitude, cellExtentInLongitude)` allows the geographic cell extents to be set precisely. If necessary, `georefcells` adjusts the geographic limits slightly to ensure an integer number of cells in each dimension.

`R = georefcells(latlim, lonlim, ____, Name, Value)` allows the directions of the columns and rows to be specified via name-value pairs.

Examples

Construct Referencing Object for Global Raster

Construct a referencing object for a global raster comprising a grid of 180-by-360 one-degree cells, with rows that start at longitude -180, and with the first cell located in the northwest corner.

```
latlim = [-90 90];  
lonlim = [-180 180];  
rasterSize = [180 360];
```

Create a raster referencing object by specifying the raster size.

```
R = georefcells(latlim,lonlim,rasterSize,'ColumnsStartFrom','north')
```

```
R =  
GeographicCellsReference with properties:
```

```
    LatitudeLimits: [-90 90]  
    LongitudeLimits: [-180 180]  
    RasterSize: [180 360]  
    RasterInterpretation: 'cells'  
    ColumnsStartFrom: 'north'  
    RowsStartFrom: 'west'  
    CellExtentInLatitude: 1  
    CellExtentInLongitude: 1  
    RasterExtentInLatitude: 180  
    RasterExtentInLongitude: 360  
    XIntrinsicLimits: [0.5 360.5]  
    YIntrinsicLimits: [0.5 180.5]  
    CoordinateSystemType: 'geographic'  
    AngleUnit: 'degree'
```

Obtain the same result by specifying cell extents.

```
extent = 1;
```

```
R = georefcells(latlim,lonlim,extent,extent,'ColumnsStartFrom','north')
```

```
R =  
GeographicCellsReference with properties:
```

```
    LatitudeLimits: [-90 90]  
    LongitudeLimits: [-180 180]
```

```
RasterSize: [180 360]
RasterInterpretation: 'cells'
ColumnsStartFrom: 'north'
RowsStartFrom: 'west'
CellExtentInLatitude: 1
CellExtentInLongitude: 1
RasterExtentInLatitude: 180
RasterExtentInLongitude: 360
XIntrinsicLimits: [0.5 360.5]
YIntrinsicLimits: [0.5 180.5]
CoordinateSystemType: 'geographic'
AngleUnit: 'degree'
```

Input Arguments

latlim — Latitude limits in degrees

[0.5 2.5] (default) | 1-by-2 numeric vector

Latitude limits in degrees, specified as a 1-by-2 numeric vector. The number of rows in the resulting raster is specified by `rasterSize`.

Example: `latlim = [-90 90];`

Data Types: double

lonlim — Longitude limits in degrees

[0.5 2.5] (default) | 1-by-2 numeric vector

Longitude limits in degrees, specified as a 1-by-2 numeric vector. The number of columns in the resulting raster is specified by `rasterSize`.

Example: `lonlim = [-180 180];`

Data Types: double

rasterSize — Size of the raster

[2 2] (default) | 1-by-2 numeric vector

Size of the raster, specified as a 1-by-2 numeric vector.

Example: `rasterSize = [180 360];`

Data Types: double

cellExtentInLatitude — Height of cells

1 (default) | numeric scalar

Height of cells, specified as a numeric scalar.

Example: `extent = 1.5`

Data Types: double

cellExtentInLongitude — Width of cells

1 (default) | numeric scalar

Width of cells, specified as a numeric scalar.

Example: `extent = 1.5`

Data Types: double

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, . . . , NameN, ValueN`.

Example: `R = georefcells(latlim, lonlim, rasterSize, 'ColumnsStartFrom', 'north')`

ColumnsStartFrom — Edge from which column indexing starts

'south' (default) | 'north'

Edge from which column indexing starts, specified as either 'north' or 'south'.

Example: `R = georefcells(latlim, lonlim, rasterSize, 'ColumnsStartFrom', 'north')`

Data Types: char | string

RowsStartFrom — Edge from which row indexing starts

'west' (default) | 'east'

Edge from which column indexing starts, specified as either 'east' or 'west'.

Example: R =
`georefcells(latlim, lonlim, rasterSize, 'RowsStartFrom', 'east')`

Data Types: `char` | `string`

Output Arguments

R — Object that references raster cells to geographic coordinates

`GeographicCellsReference` raster reference object

Object that references raster cells to geographic coordinates, returned as a `GeographicCellsReference` raster reference object.

Tips

- To construct a geographic raster reference object from a world file matrix, use the `georasterref` function.

See Also

`GeographicCellsReference` | `georefpostings` | `maprefcells`

Introduced in R2015b

geoshape

Geographic shape vector

Description

A geoshape vector is an object that represents geographic vector features with either point, line, or polygon topology. The features consist of latitude and longitude coordinates and associated attributes.

Attributes that vary spatially are termed Vertex properties. These elements of the geoshape vector are coupled such that the length of the latitude and longitude coordinate property values are always equal in length to any additional dynamic Vertex properties.

Attributes that only pertain to the overall feature (point, line, polygon) are termed Feature properties. Feature properties are not linked to the autosizing mechanism of the Vertex properties. Both property types can be added to a geoshape vector during construction or by using standard dot (.) notation after construction.

Creation

Syntax

```
s = geoshape()  
s = geoshape(latitude, longitude)  
s = geoshape(latitude, longitude, Name, Value)  
s = geoshape(structArray)  
s = geoshape(latitude, longitude, structArray)
```

Description

`s = geoshape()` constructs an empty geoshape vector, `s`, with these default property settings.

`s =`

0x1 geoshape vector with properties:

```
Collection properties:
  Geometry: 'line'
  Metadata: [1x1 struct]
Vertex properties:
  Latitude: []
  Longitude: []
```

`s` is always a column vector.

`s = geoshape(latitude, longitude)` sets the `Latitude` and `Longitude` properties of geoshape vector `s`.

`s = geoshape(latitude, longitude, Name, Value)` sets the `Latitude` and `Longitude` properties, then adds dynamic properties to the geoshape vector using `Name, Value` argument pairs. You can specify several name-value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

`s = geoshape(structArray)` constructs a geoshape vector from the fields of the structure array, `structArray`.

- If `structArray` contains the field `Lat`, and does not contain the field `Latitude`, then the `Latitude` property values are set equal to the `Lat` field values. Similar behavior occurs when `structArray` contains the field `Lon` and does not contain the field `Longitude`.
- If `structArray` contains both `Lat` and `Latitude` fields, then the `Latitude` property values are set equal to the `Latitude` field values. Also, a `Lat` dynamic property is created and its values are set equal to the `Lat` field values. Similar behavior occurs for `Lon` and `Longitude` fields when both are present in `structArray`.
- Other `structArray` fields are assigned to `s` and become dynamic properties. Field values in `structArray` that are not numeric values, string scalars, string arrays, character vectors, logical, or cell arrays of numeric values, logical, or character vectors are ignored.

`s = geoshape(latitude, longitude, structArray)` sets the `Latitude` and `Longitude` properties, and sets dynamic properties from the field values of `structArray`.

- If `structArray` contains the fields `Lat`, `Latitude`, `Lon` or `Longitude`, then those field values are ignored since the `latitude` and `longitude` input vectors set the `Latitude` and `Longitude` property values.

Properties

The `geoshape` class is a general class that represents various geographic features. This class permits features to have more than one vertex and can thus represent lines and polygons in addition to multipoints. For more about the property types in `geoshape`, see “Collection Properties” on page 1-545, “Vertex Properties” on page 1-546, and “Feature Properties” on page 1-546.

Dynamic properties are new features and vertices that are added to a `geoshape` vector. You can attach dynamic properties to a `geoshape` vector during construction using a `Name, Value` argument, or after construction using dot (`.`) notation. This is similar to adding new fields to a structure. For an example of adding dynamic Feature properties, see “Construct a Geoshape Vector with Dynamic Properties” on page 1-533.

Geometry — Shape of every feature in the geoshape vector

`'line' (default) | 'point' | 'polygon'`

Shape of every feature in the `geoshape` vector, specified as `'line'`, `'point'`, or `'polygon'`. `Geometry` is a Collection property so there can be only one value per object instance and its purpose is purely informational. The three allowable values for `Geometry` do not change class behavior. The class does not validate line or polygon topologies.

Data Types: `char` | `string`

Latitude — Latitude coordinates

numeric row or column vector

Latitude coordinates, specified as a numeric row or column vector. `Latitude` is stored as a row vector. `Latitude` is a Vertex property.

Data Types: `double` | `single`

Longitude — Longitude coordinates

numeric row or column vector

Longitude coordinates, specified as a row or column vector. `Longitude` is stored as a row vector. `Longitude` is a Vertex property.

Data Types: `double` | `single`

Metadata — Information for every feature

scalar structure

Information for every feature, specified as a scalar structure. You can add any data type to the structure. `Metadata` is a Collection property, so only one instance per object is allowed.

- If `'Metadata'` is provided as a dynamic property name in the constructor, and the corresponding value is a scalar structure, then the `Value` is copied to the `Metadata` property. Otherwise, an error is issued.
- If a `Metadata` field is provided by `structArray`, and both `Metadata` and `structArray` are scalar structures, then the `Metadata` field value is copied to the `Metadata` property value. If `structArray` is a scalar but the `Metadata` field is not a structure, then an error is issued. If `structArray` is not scalar, then the `Metadata` field is ignored.

Data Types: `struct`

Object Functions

| | |
|-------------------------|---|
| <code>append</code> | Append features to geographic or planar vector |
| <code>cat</code> | Concatenate geographic or planar vector |
| <code>disp</code> | Display geographic or planar vector |
| <code>fieldnames</code> | Return dynamic property names of geographic or planar vector |
| <code>isempty</code> | Determine if geographic or planar vector is empty |
| <code>isfield</code> | Determine if dynamic property exists in geographic or planar vector |
| <code>isprop</code> | Determine if property exists in geographic or planar vector |
| <code>length</code> | Return number of elements in geographic or planar vector |
| <code>properties</code> | Return property names of geographic or planar vector |
| <code>rmfield</code> | Remove dynamic property from geographic or planar vector |
| <code>rmprop</code> | Remove property from geographic or planar vector |
| <code>size</code> | Return size of geographic or planar vector |
| <code>struct</code> | Convert geographic or planar vector to scalar structure |
| <code>vertcat</code> | Vertically concatenate geographic or planar vectors |

Examples

Construct a Default Geoshape Vector, Then Add Properties

Construct an empty geoshape vector.

```
s = geoshape()

s =

0x1 geoshape vector with properties:

Collection properties:
  Geometry: 'line'
  Metadata: [1x1 struct]
Vertex properties:
  Latitude: []
  Longitude: []
```

Set the `Latitude` and `Longitude` property values using dot notation.

```
s.Latitude = 0:45:90;
s.Longitude = [10 10 10];
```

Display the updated geoshape vector.

```
s

s =

1x1 geoshape vector with properties:

Collection properties:
  Geometry: 'line'
  Metadata: [1x1 struct]
Vertex properties:
  Latitude: [0 45 90]
  Longitude: [10 10 10]
```

Construct a geoshape Vector Specifying Latitude and Longitude Values

Create a geoshape vector specifying latitude and longitude values as input arguments.

```
s = geoshape([42 43 45], [10 11 15])

s =

1x1 geoshape vector with properties:

Collection properties:
```

```

    Geometry: 'line'
    Metadata: [1x1 struct]
Vertex properties:
    Latitude: [42 43 45]
    Longitude: [10 11 15]

```

Construct a Geoshape Vector with Dynamic Properties

Create a geoshape vector using a Name-Value pair to define a new Feature property. This example defines a property called 'Temperature' and assigns it the value 89.

```
point = geoshape(42, -72, 'Temperature', 89)
```

```

point =
    1x1 geoshape vector with properties:

    Collection properties:
        Geometry: 'line'
        Metadata: [1x1 struct]
    Vertex properties:
        Latitude: 42
        Longitude: -72
    Feature properties:
        Temperature: 89

```

To add dynamic properties to a geoshape vector after it has been constructed, use standard dot notation. Add a dynamic property called 'TemperatureUnits' with the value 'Fahrenheit'.

```

point.TemperatureUnits = 'Fahrenheit'

point =
    1x1 geoshape vector with properties:

    Collection properties:
        Geometry: 'line'
        Metadata: [1x1 struct]
    Vertex properties:
        Latitude: 42
        Longitude: -72

```

```
Feature properties:
  Temperature: 89
  TemperatureUnits: 'Fahrenheit'
```

To modify properties, use standard dot notation. Update the temperature, and change 'Geometry' to 'point'.

```
point.Temperature = 86;
point.Geometry = 'point'
```

```
point =
  1x1 geoshape vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Vertex properties:
  Latitude: 42
  Longitude: -72
Feature properties:
  Temperature: 86
  TemperatureUnits: 'Fahrenheit'
```

Construct a Geoshape Vector from a Structure Array

This example highlights the two ways by which a geoshape vector with the same features can be created. The first way uses a structure array in the constructor for a geoshape vector. The second way adds fields of the structure array to a geoshape vector after construction.

First, read data into a structure array. The array in this example contains 128 elements. Each element defines a river as a line using multiple location vertices.

```
structArray = shaperead('worldrivers', 'UseGeoCoords', true);
```

Display the first element in `structArray`. Note that the `Lat` and `Lon` vectors are terminated with a `NaN` delimiter, which separates the `Vertex` feature data in the geoshape class.

```
structArray(1)
```



```
ans = struct with fields:
    Geometry: 'Line'
    BoundingBox: [2x2 double]
        Lon: [126.7796 126.5321 126.3121 126.2383 126.0362 NaN]
        Lat: [73.4571 73.0669 72.8343 72.6010 72.2894 NaN]
    Name: 'Lena'
```

Method 1: Provide the structure as an argument to the constructor that builds the geoshape vector.

Create a geoshape vector, providing the structure array as an argument to the constructor.

```
shape1 = geoshape(structArray)

shape1 =
    128x1 geoshape vector with properties:

    Collection properties:
        Geometry: 'line'
        Metadata: [1x1 struct]
    Vertex properties:
        (128 features concatenated with 127 delimiters)
        Latitude: [1x5542 double]
        Longitude: [1x5542 double]
    Feature properties:
        Name: {1x128 cell}
```

Note that the `BoundingBox` field in `structArray` does not get assigned to a property in `shape1` because the field value is not a supported type.

Method 2: Add features to a geoshape vector after construction.

Create an empty geoshape vector.

```
shape2 = geoshape;
```

Add the Vertex properties `Latitude` and `Longitude` from each entry in the structure array using dot notation. Add a dynamic Feature property, `RiverName`, the name of the river from each entry in `structArray`. Since the default value of the `Geometry` Collection property is `'line'` there is no need to set it explicitly in this example.

```
shape2.Latitude = {structArray.Lat};
shape2.Longitude = {structArray.Lon};
shape2.RiverName = {structArray.Name}

shape2 =
  128x1 geoshape vector with properties:

  Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
  Vertex properties:
    (128 features concatenated with 127 delimiters)
    Latitude: [1x5542 double]
    Longitude: [1x5542 double]
  Feature properties:
    RiverName: {1x128 cell}
```

Construct a Geoshape Vector Using Cell Arrays

First, read data into a structure array. The array in this example contains 128 elements. Each element defines a river as a line using multiple location vertices.

```
structArray = shaperead('worldrivers', 'UseGeoCoords', true)
```

```
structArray = 128x1 struct array with fields:
  Geometry
  BoundingBox
  Lon
  Lat
  Name
```

Create latitude and longitude vectors. For illustrative purposes, the vectors do not correspond to the elements of `structArray`.

```
lat = {[0:10:40], [1:5]};
lon = {[ -60:30:60], [0:2:8]};
```

Construct a geoshape vector using the latitude and longitude vectors and the structure array.

```
s = geoshape(lat,lon,structArray);
```

Display the first three elements of `s`. Features are separated with a NaN delimiter.

```
s(1:3)
ans =
  3x1 geoshape vector with properties:

  Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
  Vertex properties:
    (3 features concatenated with 2 delimiters)
    Latitude: [0 10 20 30 40 NaN 1 2 3 4 5 NaN 0]
    Longitude: [-60 -30 0 30 60 NaN 0 2 4 6 8 NaN 0]
  Feature properties:
    Name: {'Lena' 'Lena' 'Mackenzie'}
```

Observe that `geoshape` uses the arguments `lat` and `lon` to populate the `Latitude` and `Longitude` properties, even though `structArray` provides `Lat` and `Lon` field values. Also, since `lat` and `lon` have fewer elements than features in `structArray`, the `Latitude` and `Longitude` properties expand in size using a value of 0.

Use Indexing to Append a Single Point and a Shape to a Geoshape Vector

Create a `geoshape` vector containing a single feature of the locations of world cities.

```
S = shaperead('worldcities.shp', 'UseGeoCoords', true);
cities = geoshape([S.Lat], [S.Lon], 'Name', {{S.Name}});
cities.Geometry = 'point';
```

Append Paderborn Germany to the `geoshape` vector.

```
lat = 51.715254;
lon = 8.75213;
cities(1).Latitude(end+1) = lat;
cities(1).Longitude(end) = lon;
cities(1).Name{end} = 'Paderborn'
```

```
cities =
  1x1 geoshape vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Vertex properties:
  Latitude: [1x319 double]
  Longitude: [1x319 double]
  Name: {1x319 cell}
```

The length of each vertex property grows by one when `Latitude(end+1)` is set. The remaining properties are indexed with `end`.

You can display the last point by constructing a `geopoint` vector.

```
paderborn = geopoint(cities.Latitude(end), cities.Longitude(end), ...
  'Name', cities.Name{end})
```

```
paderborn =
```

```
1x1 geopoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  Latitude: 51.7153
  Longitude: 8.7521
  Name: 'Paderborn'
```


Create a `geoshape` vector with two new features containing the cities in the northern and southern hemispheres. Add a `Location` dynamic Feature property to distinguish the different classifications.

```
northern = cities(1).Latitude >= 0;
southern = cities(1).Latitude < 0;
index = {northern; southern};
location = {'Northern Hemisphere', 'Southern Hemisphere'};
hemispheres = geoshape();
for k = 1:length(index)
    hemispheres = append(hemispheres, ...
        cities.Latitude(index{k}), cities.Longitude(index{k}), ...
        'Name', {cities.Name(index{k})}, 'Location', location{k});
end
hemispheres.Geometry = 'point'
```

```
hemispheres =  
  
2x1 geoshape vector with properties:  
  
Collection properties:  
    Geometry: 'point'  
    Metadata: [1x1 struct]  
Vertex properties:  
    (2 features concatenated with 1 delimiter)  
    Latitude: [1x320 double]  
    Longitude: [1x320 double]  
    Name: {1x320 cell}  
Feature properties:  
    Location: {'Northern Hemisphere' 'Southern Hemisphere'}
```

Plot the northern cities in red and the southern cities in blue.

```
hemispheres.Color = {'red', 'blue'};  
figure;worldmap('world')  
geoshow('landareas.shp')  
for k=1:2  
    geoshow(hemispheres(k).Latitude, hemispheres(k).Longitude, ...  
            'DisplayType', hemispheres.Geometry, ...  
            'MarkerEdgeColor', hemispheres(k).Color)  
end
```



Use Indexing to Sort and Modify Dynamic Features

Construct a geoshape vector and sort its dynamic properties.

```
shape = geoshape(shaperead('tsunamis', 'UseGeoCoords', true));  
shape.Geometry = 'point';  
shape = shape(:, sort(fieldnames(shape)))
```

```
shape =
```

```
162x1 geoshape vector with properties:
```

```

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Vertex properties:
  (162 features concatenated with 161 delimiters)
  Latitude: [1x323 double]
  Longitude: [1x323 double]
Feature properties:
  Cause: {1x162 cell}
  Cause_Code: [1x162 double]
  Country: {1x162 cell}
  Day: [1x162 double]
  Desc_Deaths: [1x162 double]
  Eq_Mag: [1x162 double]
  Hour: [1x162 double]
  Iida_Mag: [1x162 double]
  Intensity: [1x162 double]
  Location: {1x162 cell}
  Max_Height: [1x162 double]
  Minute: [1x162 double]
  Month: [1x162 double]
  Num_Deaths: [1x162 double]
  Second: [1x162 double]
  Val_Code: [1x162 double]
  Validity: {1x162 cell}
  Year: [1x162 double]

```

Modify the geoshape vector to contain only the dynamic properties, Year, Month, Day, Hour, Minute.

```
shape = shape(:, {'Year', 'Month', 'Day', 'Hour', 'Minute'})
```

```
shape =
```

```
162x1 geoshape vector with properties:
```

```

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Vertex properties:
  (162 features concatenated with 161 delimiters)
  Latitude: [1x323 double]
  Longitude: [1x323 double]
Feature properties:

```

```
Year: [1x162 double]
Month: [1x162 double]
Day: [1x162 double]
Hour: [1x162 double]
Minute: [1x162 double]
```

Display the first five elements.

```
shape(1:5)
```

```
ans =
```

```
5x1 geoshape vector with properties:
```

```
Collection properties:
```

```
Geometry: 'point'
```

```
Metadata: [1x1 struct]
```

```
Vertex properties:
```

```
(5 features concatenated with 4 delimiters)
```

```
Latitude: [-3.8000 NaN 19.5000 NaN -9.0200 NaN 42.1500 NaN 19.1000]
```

```
Longitude: [128.3000 NaN -156 NaN 157.9500 NaN 143.8500 NaN -155]
```

```
Feature properties:
```

```
Year: [1950 1951 1951 1952 1952]
```

```
Month: [10 8 12 3 3]
```

```
Day: [8 21 22 4 17]
```

```
Hour: [3 10 NaN 1 3]
```

```
Minute: [23 57 NaN 22 58]
```

Construct a Geoshape Vector from Multiple Objects

Read multiple GPS track log data from a file. `trk1` and `trk2` are geopoint objects.

```
trk1 = gpxread('sample_tracks')
```

```
trk1 =
```

```
1851x1 geopoint vector with properties:
```

```
Collection properties:
```

```
Geometry: 'point'
```

```
Metadata: [1x1 struct]
```

```
Feature properties:
```

```
Latitude: [1x1851 double]
```

```
Longitude: [1x1851 double]
```



```
Elevation: [1x1851 double]
Time: {1x1851 cell}
```

```
trk2 = gpxread('sample_tracks', 'Index', 2);
```

To construct a geoshape vector with multiple features, place the coordinates into cell arrays.

```
lat = {trk1.Latitude, trk2.Latitude};
lon = {trk1.Longitude, trk2.Longitude};
```

Place the elevation and time values into cell arrays.

```
elevation = {trk1.Elevation, trk2.Elevation};
time = {trk1.Time, trk2.Time};
```

Construct a geoshape vector containing two track log features that include Elevation and Time as dynamic Vertex properties.

```
tracks = geoshape(lat, lon, 'Elevation', elevation, 'Time', time)
```

```
tracks =
  2x1 geoshape vector with properties:

  Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
  Vertex properties:
    (2 features concatenated with 1 delimiter)
    Latitude: [1x2591 double]
    Longitude: [1x2591 double]
    Elevation: [1x2591 double]
    Time: {1x2591 cell}
```

Each Latitude and Longitude coordinate pair has associated Elevation and Time values.

To construct a geoshape vector containing a dynamic Feature property, use an array that is the same length as the coordinate cell array. For example, add a MaximumElevation dynamic Feature property.

```
tracks.MaximumElevation = [max(trk1.Elevation) max(trk2.Elevation)]
```

```
tracks =
  2x1 geoshape vector with properties:

  Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
  Vertex properties:
    (2 features concatenated with 1 delimiter)
    Latitude: [1x2591 double]
    Longitude: [1x2591 double]
    Elevation: [1x2591 double]
    Time: {1x2591 cell}
  Feature properties:
    MaximumElevation: [92.4240 76.1000]
```

The Feature property value has only two numeric values, one for each feature.

Store Latitude and Longitude Values in Geoshape Vector

Load coastline data from a MAT-file.

```
load coastlines
```

Create an n -by-2 array of coastline latitude and longitude values.

```
pts = [coastlat coastlon];
```

Create a geoshape object and store the latitude and longitude data. If you store latitude and longitude coordinate values in an n -by-2 array, `geoshape` assigns the `Latitude` property values to the first **column** and the `Longitude` property values to the second **column**.

```
shape = geoshape();
shape(1) = pts
```

```
shape =
  1x1 geoshape vector with properties:

  Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
```

```
Vertex properties:  
  Latitude: [1x9865 double]  
  Longitude: [1x9865 double]
```

Note that `Latitude` and `Longitude` are stored as row vectors in the `geoshape` vector.

Now, create a 2-by- m array of coastline latitude and longitude values. Note the semicolon inside the brackets.

```
pts2 = [coastlat; coastlon];
```

Create a `geoshape` object and store the latitude and longitude data. If you store latitude and longitude coordinate values in a 2-by- m array, `geoshape` assigns the `Latitude` property values to the first **row** and the `Longitude` property values to the second **row**.

```
shape2 = geoshape();  
shape2(1) = pts2
```

```
shape2 =  
  1x1 geoshape vector with properties:
```

```
Collection properties:  
  Geometry: 'line'  
  Metadata: [1x1 struct]  
Vertex properties:  
  Latitude: [1x19730 double]  
  Longitude: [1x19730 double]
```

Definitions

Collection Properties

Collection properties contain only one value per class instance. In contrast, the `Feature` and `Vertex` property types have attribute values associated with each feature or with each vertex in a set that defines a feature. `Geometry` and `Metadata` are the only two Collection properties.

Vertex Properties

Vertex properties provide a scalar number or a character vector for each vertex in a geoshape object. Vertex properties are suitable for attributes that vary spatially from point to point (vertex to vertex) along a line. Examples of such spatially varying attributes could be elevation, speed, temperature, or time. `Latitude` and `Longitude` are vertex properties since they contain a scalar number for each vertex in a geoshape vector.

Attribute values are associated with each vertex during construction or by using dot notation after construction. This process is similar to adding dynamic fields to a structure. Dynamic Vertex property values of an individual feature match its `Latitude` and `Longitude` values in length.

Feature Properties

Feature properties provide one value (a scalar number, scalar string, or character vector) for each feature in a geoshape vector. They are suitable for properties, such as name, owner, serial number, or age, that describe a given feature (an element of a geoshape vector) as a whole. Like Vertex properties, Feature properties can be added during construction or by using dot notation after construction.

Tips

- If `Latitude`, `Longitude`, or a dynamic property is set with more values than features in the geoshape vector, then all other properties expand in size using 0 for numeric values and an empty character vector (' ') for cell values.
- If a dynamic property is set with fewer values than the number of features, then this dynamic property expands to match the size of the other properties, by inserting a 0 if the value is numeric or an empty character vector (' '), if the value is a cell array.
- If the `Latitude` or `Longitude` property of the geoshape vector is set with fewer values than contained in the object, then all other properties shrink in size.
- If either `Latitude` or `Longitude` are set to [], then both coordinate properties are set to [] and all dynamic properties are removed.
- If a dynamic property is set to [], then it is removed from the object.
- The geoshape vector can be indexed like any MATLAB vector. You can access any element of the vector to obtain a specific feature. The following examples demonstrate this behavior:

“Use Indexing to Append a Single Point and a Shape to a Geoshape Vector” on page 1-537

“Use Indexing to Sort and Modify Dynamic Features” on page 1-540

“Construct a Geoshape Vector from Multiple Objects” on page 1-542

See Also

Functions

gpxread | shaperead

Objects

geopoint | mappoint | mapshape

Introduced in R2012a

- If `S` is a `mappoint` vector, a `mapshape` vector, or a `mapstruct` (with 'X' and 'Y' fields), then `geoshow` plots vertices as (pre-projected) map coordinates and issues a warning.

You can optionally specify symbolization rules using the `SymbolSpec` name-value pair argument.

`geoshow(lat, lon, Z)` projects and displays the geolocated data grid, `Z`. In this syntax, `lat` and `lon` are M-by-N latitude-longitude arrays. `Z` is an M-by-N array of class `double`. You can optionally display the data as a surface, mesh, texture map, or contour by using the `DisplayType` name-value pair argument.

`geoshow(Z, R)` projects and displays a regular data grid, `Z`, with referencing object `R`. You can optionally display the data as a surface, mesh, texture map, or contour by using the `DisplayType` name-value pair argument. If `DisplayType` is 'texturemap', then `geoshow` constructs a surface with `ZData` values set to 0.

`geoshow(lat, lon, I)` and

`geoshow(lat, lon, X, cmap)` projects and displays a geolocated image as a texture map on a zero-elevation surface. The geolocated image `I` can be a `truecolor`, `grayscale`, or `binary` image. `X` is an indexed image with `colormap` `cmap`. Examples of geolocated images include a color composite from a satellite swath or an image originally referenced to a different coordinate system.

`geoshow(I, R)` and

`geoshow(X, cmap, R)` project and display an image georeferenced to latitude-longitude through the referencing object `R`. The image is shown as a texture map on a zero-elevation surface.

`geoshow(filename)` projects and displays data from the file specified according to the type of file format.

`geoshow(____, Name, Value)` specifies parameters and corresponding values that modify the type of display or set MATLAB graphics properties. You can use name,value pairs to set:

- `Name, Value` arguments
- Any MATLAB Graphics line, patch, and surface properties
- Any Mapping Toolbox contour properties

Parameter names can be abbreviated, and case does not matter.

`geoshow(ax, ___)` sets the parent axes to `ax`.


`h = geoshow(___)` returns a handle to a MATLAB graphics object.

Examples

Display World Land Areas Using Plate Carree Projection

Display map of the world using default Plate Carree projection.


```
figure  
geoshow('landareas.shp', 'FaceColor', [0.5 1.0 0.5]);
```

Use Symbolspec to Define Face Colors and Set Default Face Colors

Set up an empty map axes with projection and limits suitable for displaying all 50 states.

```
figure  
worldmap('na');
```



Read USA high resolution data.


```
states = shaperead('usastatehi', 'UseGeoCoords', true);
```

Create a symbolspec that sets the color of Alaska and Hawaii polygons red.

```
symspec = makesymbolspec('Polygon', ...  
    {'Name', 'Alaska', 'FaceColor', 'red'}, ...  
    {'Name', 'Hawaii', 'FaceColor', 'red'});
```

Display all the other states, setting the default FaceColor property to blue and the default EdgeColor property to black.

```
geoshow(states, 'SymbolSpec', symspec, ...  
         'DefaultFaceColor', 'blue', ...  
         'DefaultEdgeColor', 'black');
```



Create Map of Korea and Display Data Grid as Texture Map


Display a map, using the `geoshow` function with the `'DisplayType'` parameter set to `'TextureMap'`.

Load MAT file containing map information about Korean peninsula.

```
load korea
```


Set up an empty map axes with projection and limits for the Korean peninsula.

```
figure;  
worldmap(map, refvec)
```




Display the Korean data grid as a texture map.

```
geoshow(gca, map, refvec, 'DisplayType', 'texturemap');  
demcmap(map)
```



Display the land area boundary as a black line.

```
S = shaperead('landareas','UseGeoCoords',true);  
geoshow([S.Lat], [S.Lon],'Color','black');
```



Create Map of Korea and Display NaNs as Transparent

Display a map, interpreting NaNs as transparent. This example uses the `geoshow` function with the `'DisplayType'` parameter set to `'surface'`.

Load map of Korean peninsula.

```
korea = load('korea');  
Z = korea.map;
```

Insert an band of null values using NaNs.


```
Z(80:100,:) = NaN;
```

Create a raster reference object.

```
R = georasterref('RasterSize',size(Z),...  
    'Latlim',[30 45], 'Lonlim', [115 135]);
```

Display world map with NaN values displayed as transparent. Note that the settings for ZData and CData ensure that the resulting surface falls in the $z == 0$ plane, instead of being 3-dimensional.

```
figure;  
worldmap(Z,R)  
geoshow(Z,R,'DisplayType','surface','ZData',zeros(size(Z)),'CData',Z)  
demcmap(Z)
```




Display EGM96 Geoid Heights Masking Out Land Areas

Load geoid and display.

```
load geoid
```


Create a figure with an Eckert projection.

```
figure  
axesm eckert4;  
framem; gridm;  
axis off
```




Display the geoid as a texture map.

```
geoshow(geoid, geoidrefvec, 'DisplayType', 'texturemap');
```




Create a colorbar and title.

```
hcb = colorbar('southoutside');  
set(get(hcb, 'Xlabel'), 'String', 'EGM96 Geoid Heights in Meters.')
```



Mask out all the land.

```
geoshow('landareas.shp', 'FaceColor', 'black');
```




Display EGM96 Geoid Heights as 3-D Surface Using Eckert IV Projection

Create the figure with an Eckert projection.

```
figure  
axesm eckert4  
axis off
```


Load the geoid, and display it as a surface.

```
load geoid  
h = geoshow(geoid, geoidrefvec, 'DisplayType','surface');
```




Add light and material.

```
light  
material(0.6*[ 1 1 1])
```



View the map as a 3-D surface.

```
view(3)  
axis normal  
tightmap
```




Display Moon Albedo Using Plate Carree Projection and Orthographic Projection

Load the moon albedo image.

```
load moonalb
```

Project and display the moon albedo image using a default Plate Carree projection.

```
figure  
geoshow(moonalb,moonal BrefVec)
```



Project and display the moon albedo image as a texture map in an orthographic projection.

```
figure
axesm ortho
geoshow(moonalb,moonalbfvec,'DisplayType','texturemap')
colormap(gray(256))
axis off
```



Display Digital Elevation Model as Texture Map and in 3-D

Unzip a USGS 24K digital elevation model (DEM) file into a temporary file. The toolbox includes a San Francisco South 24K DEM file.

```
filenames = gunzip('sanfranciscos.dem.gz',tempdir);  
demFilename = filenames{1};
```

Read every other point of the 1:24,000 DEM file.

```
[lat,lon,Z,header,profile] = usgs24kdem(demFilename,2);
```


Delete the temporary file.

```
delete(demFilename);
```

Because no negative elevations exist, move all points at sea level to -1 to color them blue.

```
Z(Z==0) = -1;
```

Compute the latitude and longitude limits for the DEM.

```
latlim = [min(lat(:)) max(lat(:))]
```

```
latlim = 1×2
```

```
37.6249 37.7504
```

```
lonlim = [min(lon(:)) max(lon(:))]
```

```
lonlim = 1×2
```

```
-122.5008 -122.3740
```

Display the DEM values as a texture map.

```
figure
```

```
usamap(latlim, lonlim)
```


```
geoshow(lat, lon, Z, 'DisplayType', 'texturemap')
```

```
demcmap(Z)
```

```
daspectm('m',1)
```


Overlay black contour lines onto the texture map.

```
geoshow(lat, lon, Z, 'DisplayType', 'contour', ...  
        'LineColor', 'black');
```



View the DEM values in 3-D.

```
figure
usamap(latlim, lonlim)
geoshow(lat,lon,Z,'DisplayType','surface')
demcmap(Z)
daspectm('m',1)
view(3)
```



Input Arguments

lat, lon — Latitude or longitude data

numeric vector | M -by- N numeric array

Latitude or longitude data, specified as a numeric vector or an M -by- N numeric matrix.

- `lat` and `lon` are vectors when used with the syntax `geoshow(lat, lon)`.
- `lat` and `lon` are 2-D arrays when used with the `geoshow(lat, lon, Z)` syntax, the `geoshow(lat, lon, I)` syntax, or the `geoshow(lat, lon, X, cmap)` syntax. If `lat` and `lon` are matrices, they represent coordinate arrays or a geolocation array in

geographic coordinates, and must be the same size as Z, I, or X. If I is an RGB image, `lat` and `lon` must be matrices that match the first two dimensions of the image.

`lat` and `lon` may contain embedded NaNs to delimit individual lines or polygon parts.

S — Geographic features

geographic data structure | dynamic vector

Geographic features, specified as a geographic data structure or dynamic vector.

Z — Data grid

M-by-*N* numeric array

Data grid, specified as an *M*-by-*N* numeric array that may contain NaN values. Z is either a georeferenced data grid, or a regular data grid associated with a geographic reference R.

R — Geographic reference

geographic raster reference object | vector | matrix

Geographic reference, specified as one of the following. For more information about referencing vectors and matrices, see “Georeferenced Raster Data”.

| Type | Description |
|------------------------------------|---|
| Geographic raster reference object | <p>GeographicCellsReference or GeographicPostingsReference geographic raster reference object that relates the subscripts of Z to geographic coordinates. The RasterSize property must be consistent with the size of the data grid, <code>size(Z)</code>.</p> <p>If R is a GeographicPostingsReference object, then the 'image' and 'texturemap' values of DisplayType are not accepted.</p> |
| Vector | <p>1-by-3 numeric vector with elements:</p> <p>[cells/degree northern_latitude_limit western_longitude_lim</p> |

| Type | Description |
|--------|---|
| Matrix | <p>3-by-2 numeric matrix that transforms raster row and column indices to or from geographic coordinates according to:</p> $[\text{lon } \text{lat}] = [\text{row } \text{col } 1] * R$ <p>R defines a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. Nearest-neighbor interpolation is used by default. NaN is returned for points outside the grid limits or for which <code>lat</code> or <code>lon</code> contain NaN. All angles are in units of degrees.</p> |

I — Truecolor, grayscale, or binary image

M-by-*N*-by-3 array | *M*-by-*N* array

Truecolor, grayscale, or binary image, specified as an *M*-by-*N*-by-3 array for truecolor images, or an *M*-by-*N* array for grayscale or binary images. `lat` and `lon` must be *M*-by-*N* arrays. If specified, 'DisplayType' must be set to 'image'.

X — Indexed image

M-by-*N* array

Indexed image with color map defined by `cmap`, specified as an *M*-by-*N* array. `lat` and `lon` must be *M*-by-*N* arrays. If specified, 'DisplayType' must be set to 'image'.

cmap — Color map

c-by-3 matrix

Color map of indexed image *X*, specified as an *c*-by-3 numeric matrix. There are *c* colors in the color map, each represented by a red, green, and blue pixel value.

filename — File name

character vector | string scalar

File name, specified as a string scalar or character vector. `geoshow` automatically sets the `DisplayType` parameter according to the format of the data.

| Format | DisplayType |
|---------------------------------|---|
| Shape file | 'point', 'multipoint', 'line', or 'polygon' |
| GeoTIFF | 'image' |
| TIFF/JPEG/PNG with a world file | 'image' |
| ARC ASCII GRID | 'surface' (can be overridden) |
| SDTS raster | 'surface' (can be overridden) |

Data Types: char | string

ax — Parent axes

axes object

Parent axes, specified as an axes object.

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

Example: 'DisplayType', 'point'

SymbolSpec — Symbolization rules

structure

Symbolization rules to be used for displaying vector data, specified as the comma-separated pair consisting of 'SymbolSpec' and a structure returned by `makesymbolspec`. It is used only for vector data stored in geographic data structures. In cases where both `SymbolSpec` and one or more graphics properties are specified, the graphics properties override any settings in the `symbolspec` structure.

To change the default symbolization rule for a `Name`, `Value` pair in the `SymbolSpec` structure, prefix the word 'Default' to the graphics property name.

DisplayType — Display type

'point' | 'multipoint' | 'line' | 'polygon' | 'image' | 'surface' | 'mesh' | 'texturemap' | 'contour'

Type of graphic display for the data, specified as the comma-separated pair consisting of 'DisplayType' and one of the following values.

| Data Type | Display Type | Type of Property |
|-----------|--------------|--------------------|
| Vector | 'point' | <i>line marker</i> |
| | 'multipoint' | <i>line marker</i> |
| | 'line' | <i>line</i> |
| | 'polygon' | <i>patch</i> |
| Image | 'image' | <i>surface</i> |
| Grid | 'surface' | <i>surface</i> |
| | 'mesh' | <i>surface</i> |
| | 'texturemap' | <i>surface</i> |
| | 'contour' | <i>contour</i> |

Valid values of `DisplayType` depend on the format of the map data. For example, if the map data is a geolocated image or georeferenced image, then the only valid value of `DisplayType` is 'image'. Different display types support different geographic data class types:

| Display Type | Supported Class Types |
|--------------|------------------------------------|
| Image | logical, uint8, uint16, and double |
| Surface | single and double |
| Texture map | All numeric types and logical |

Output Arguments

h — Parent axes

handle object | modified patch object

Parent axes, returned as a handle to a MATLAB graphics object or, in the case of polygons, a modified patch object. If a geostruct or shapefile name is input, `geoshow` returns the handle to an `hggroup` object with one child per feature in the geostruct or shapefile, excluding any features that are completely trimmed away. In the case of a polygon geostruct or shapefile, each child is a modified patch object; otherwise it is a line object.

Tips

- When calling `shaperead` to read files that contain coordinates in latitude and longitude, be sure to specify the `shaperead` argument pair `'UseGeoCoords', true`. If you do not include this argument, `shaperead` will create a `mapstruct`, with coordinate fields labelled `X` and `Y` instead of `Lon` and `Lat`. In such cases, `geoshow` assumes that the `geostruct` is in fact a `mapstruct` containing projected coordinates, warns, and calls `mapshow` to display the `geostruct` data without projecting it.
- If you do not want `geoshow` to draw on top of an existing map, create a new figure or subplot before calling it.
- When you display vector data in a map axes using `geoshow`, you should not subsequently change the map projection using `setm`. You can, however, change the projection with `setm` for raster data. For more information, see “Change Map Projections Using `geoshow`”.
- If you display a polygon, do not set `'EdgeColor'` to either `'flat'` or `'interp'`. This combination may result in a warning.
- When projecting data onto a map axes, `geoshow` uses the projection stored with the map axes. When displaying on a regular axes, it constructs a default Plate Carrée projection with a scale factor of $180/\pi$, enabling direct readout of coordinates in degrees.
- `geoshow` can generally be substituted for `displaym`. However, there are limitations where display of specific objects is concerned. See the remarks under `updategeostruct` for further information.
- When you display raster data in a map using `geoshow`, columns near the eastern or western edge may fail to display. This is seldom noticeable, except when the raster is very coarse relative to the displayed area. To include additional columns in the display, it might help to:
 - Resize the grid to a finer mesh.
 - Make sure the cell boundaries and map limits align.
 - Expand the map limits.

See Also

Functions

`axesm` | `makesymbolspec` | `mapshow` | `mapview` | `updategeostruct`

Objects

GeographicCellsReference | GeographicPostingsReference

Introduced before R2006a

map.geotiff.RPCCoefficientTag

Create a Rational Polynomial Coefficients Tag object

Syntax

```
rpctag = map.geotiff.RPCCoefficientTag
rpctag = map.geotiff.RPCCoefficientTag(tiffTagValue)
```

Description

`rpctag = map.geotiff.RPCCoefficientTag` creates a default `RPCCoefficientTag` object.

`rpctag = map.geotiff.RPCCoefficientTag(tiffTagValue)` creates an `RPCCoefficientTag` object and sets the property values to the corresponding values in the 92-element vector specified in `tiffTagValue`.

Examples

Create `RPCCoefficientTag` Object with Default Properties

Call the `RPCCoefficientTag` class constructor with no arguments.

```
rpctag = map.geotiff.RPCCoefficientTag
```

```
rpctag =
  RPCCoefficientTag with properties:
```

```
    BiasErrorInMeters: -1
    RandomErrorInMeters: -1
        LineOffset: 0
        SampleOffset: 0
    GeodeticLatitudeOffset: 0
    GeodeticLongitudeOffset: 0
    GeodeticHeightOffset: 0
```

```

        LineScale: 1
        SampleScale: 1
        GeodeticLatitudeScale: 1
        GeodeticLongitudeScale: 1
        GeodeticHeightScale: 1
        LineNumeratorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
        LineDenominatorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
        SampleNumeratorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
        SampleDenominatorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]

```

Write Raw RPC Coefficient Metadata to GeoTIFF File

This example shows how to write RPC coefficient metadata to a TIFF file. In a real workflow, you would create the RPC coefficient metadata according to the TIFF extension specification. This example does not show the specifics of how to create valid RPC metadata. To simulate raw RPC metadata, the example creates a sample TIFF file with RPC metadata and then uses `imfinfo` to read this RPC metadata in raw, unprocessed form from the file. The example then writes this raw RPC metadata to a file using the `geotiffwrite` function.

Create Raw RPC Coefficient Metadata

To simulate raw RPC metadata, create a simple test file and write some RPC metadata to the file. For this test file, create a toy image and a referencing object associated with the image.

```

myimage = zeros(180,360);
latlim = [-90 90];
lonlim = [-180 180];
R = georefcells(latlim,lonlim,size(myimage));

```

Create an `RPCCoefficientTag` metadata object and set some of the fields. The toolbox uses the `RPCCoefficientTag` object to represent RPC metadata in human readable form.

```

rpctag = map.geotiff.RPCCoefficientTag;
rpctag.LineOffset = 1;
rpctag.SampleOffset = 1;
rpctag.LineScale = 2;
rpctag.SampleScale = 2;
rpctag.GeodeticHeightScale = 500;

```

Write the image, the associated referencing object, and the `RPCCoefficientTag` object to a file.

```
geotiffwrite('myfile',myimage,R,'RPCCoefficientTag',rpctag)
```

Read Raw RPC Coefficient Metadata

Read the RPC coefficient metadata from the test file using the `imfinfo` function. When it encounters unfamiliar metadata, `imfinfo` returns the data, unprocessed, in the `UnknownTags` field. Note how the `UnknownTags` field contains an array of 92 doubles. This is the raw RPC coefficient metadata, read from the file in unprocessed form.

```
info = imfinfo('myfile.tif');
info.UnknownTags

ans = struct with fields:
    ID: 50844
    Offset: 10672
    Value: [1x92 double]
```

Write Raw RPC Metadata to a File

Write the raw RPC metadata to a file. First, extract the RPC coefficient metadata from the `info` structure.

```
value = info.UnknownTags.Value;
```

Then, construct an `RPCCoefficientTag` object, passing the raw RPC metadata (array of 92 doubles) as an argument.

```
rpcdata = map.geotiff.RPCCoefficientTag(value)

rpcdata =
  RPCCoefficientTag with properties:
      BiasErrorInMeters: -1
      RandomErrorInMeters: -1
          LineOffset: 1
          SampleOffset: 1
      GeodeticLatitudeOffset: 0
      GeodeticLongitudeOffset: 0
      GeodeticHeightOffset: 0
          LineScale: 2
          SampleScale: 2
```

```

    GeodeticLatitudeScale: 1
    GeodeticLongitudeScale: 1
    GeodeticHeightScale: 500
    LineNumeratorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
    LineDenominatorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
    SampleNumeratorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
    SampleDenominatorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]

```

Pass the `RPCCoefficientTag` object to the `geotiffwrite` function and write the RPC metadata to a file.

```
geotiffwrite('myfile2',myimage,R,'RPCCoefficientTag',rpcdata)
```

To verify that the data was written to the file, read the RPC metadata from the TIFF file using `geotiffinfo`. Compare the returned RPC metadata with the metadata written to the test file.

```
ginfo = geotiffinfo('myfile2');
ginfo.GeoTIFFTags.RPCCoefficientTag
```

```
ans =
```

```
RPCCoefficientTag with properties:
```

```

    BiasErrorInMeters: -1
    RandomErrorInMeters: -1
    LineOffset: 1
    SampleOffset: 1
    GeodeticLatitudeOffset: 0
    GeodeticLongitudeOffset: 0
    GeodeticHeightOffset: 0
    LineScale: 2
    SampleScale: 2
    GeodeticLatitudeScale: 1
    GeodeticLongitudeScale: 1
    GeodeticHeightScale: 500
    LineNumeratorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
    LineDenominatorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
    SampleNumeratorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]

```

```
SampleDenominatorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
```

Input Arguments

tiffTagValue — Value of `RPCCoefficientTag` properties

92-element vector

Value of `RPCCoefficientTag` properties, specified as a 92-element vector.

Data Types: double

See Also

`RPCCoefficientTag` | `geotiffinfo` | `geotiffwrite`

Introduced in R2015b

geotiff2mstruct

Convert GeoTIFF information to map projection structure

Syntax

```
mstruct = geotiff2mstruct(proj)
```

Description

`mstruct = geotiff2mstruct(proj)` converts the GeoTIFF projection structure, `proj`, to the map projection structure, `mstruct`. The unit of length of the `mstruct` projection is meter.

The GeoTIFF projection structure, `proj`, must reference a projected coordinate system, as indicated by a value of 'ModelTypeProjected' in the `ModelType` field. If `ModelType` has the value 'ModelTypeGeographic' then it doesn't make sense to convert to a map projection structure and an error is issued.

Examples

```
% Compare inverse transform of points using projinv and minvtran.  
% Obtain the projection structure of 'boston.tif'.  
proj = geotiffinfo('boston.tif');  
  
% Convert the corner map coordinates to latitude and longitude.  
x = proj.CornerCoords.X;  
y = proj.CornerCoords.Y;  
[latProj, lonProj] = projinv(proj, x, y);  
  
% Obtain the mstruct from the GeoTIFF projection.  
mstruct = geotiff2mstruct(proj);  
  
% Convert the units of x and y to meter to match projection units.  
x = unitsratio('meter','sf') * x;  
y = unitsratio('meter','sf') * y;
```

```
% Convert the corner map coordinates to latitude and longitude.
[latMstruct, lonMstruct] = minvtran(mstruct, x, y);

% Verify the values are within a tolerance of each other.
abs(latProj - latMstruct) <= 1e-7
abs(lonProj - lonMstruct) <= 1e-7

ans =
     1     1     1     1

ans =
     1     1     1     1
```

See Also

[axesm](#) | [defaultm](#) | [geotiffinfo](#) | [projfwd](#) | [projinv](#) | [projlist](#)

Introduced before R2006a

geotiffinfo

Information about GeoTIFF file

Syntax

```
info = geotiffinfo(filename)
info = geotiffinfo(url)
```

Description

`info = geotiffinfo(filename)` returns a structure whose fields contain image properties and cartographic information about a GeoTIFF file.

`info = geotiffinfo(url)` reads the GeoTIFF image from a URL.

Examples

Return Information about Geotiff File

```
info = geotiffinfo('boston.tif')
```

```
info = struct with fields:
    Filename: 'B:\matlab\toolbox\map\mapdata\boston.tif'
    FileModDate: '13-May-2011 22:28:45'
    FileSize: 38729900
    Format: 'tif'
    FormatVersion: []
    Height: 2881
    Width: 4481
    BitDepth: 8
    ColorType: 'truecolor'
    ModelType: 'ModelTypeProjected'
        PCS: 'NAD83 / Massachusetts Mainland'
    Projection: 'SPCS83 Massachusetts Mainland zone (meters)'
    MapSys: 'STATE_PLANE_83'
```

```
        Zone: 2001
CTProjection: 'CT_LambertConfConic_2SP'
  ProjParm: [7x1 double]
  ProjParmId: {7x1 cell}
    GCS: 'NAD83'
    Datum: 'North American Datum 1983'
    Ellipsoid: 'GRS 1980'
    SemiMajor: 6378137
    SemiMinor: 6.3568e+06
    PM: 'Greenwich'
PMLongToGreenwich: 0
  UOMLength: 'US survey foot'
UOMLengthInMeters: 0.3048
  UOMAngle: 'degree'
UOMAngleInDegrees: 1
  TiePoints: [1x1 struct]
  PixelScale: [3x1 double]
  SpatialRef: [1x1 map.rasterref.MapCellsReference]
  RefMatrix: [3x2 double]
  BoundingBox: [2x2 double]
  CornerCoords: [1x1 struct]
  GeoTIFFCodes: [1x1 struct]
  GeoTIFFTags: [1x1 struct]
ImageDescription: '"GeoEye"'
```

Input Arguments

filename — Name of GeoTIFF file

character vector

Name of the GeoTIFF file, specified as a character vector. Include the folder name in `filename` or place the file in the current folder or in a folder on the MATLAB path. If the named file includes the extension `.TIF` or `.TIFF` (either upper- or lowercase), you can omit the extension from `filename`.

If the named file contains multiple GeoTIFF images, `info` is a structure array with one element for each image in the file. For example, `info(3)` would contain information about the third image in the file. If multiple images exist in the file, it is assumed that each image has the same cartographic information and image width and height.

url — Internet URL

character vector

Internet URL, specified as a character vector. The URL must include the protocol type (e.g., "http://").

Output Arguments

info — Image properties and cartographic information about a GeoTIFF file structure

Image properties and cartographic information about a GeoTIFF file, returned as a structure containing the following fields.

| Field | Description |
|---------------|--|
| Filename | Name of the file or URL |
| FileModDate | Modification date of the file |
| FileSize | Integer indicating the size of the file in bytes. |
| Format | File format (always 'tiff') |
| FormatVersion | File format version |
| Height | Integer indicating the height of the image in pixels |
| Width | Integer indicating the width of the image in pixels |
| BitDepth | Integer indicating the number of bits per pixel |
| ColorType | Type of image: 'truecolor' for a true-color (RGB) image, 'grayscale' for a grayscale image, or 'indexed' for an indexed image. |
| ModelType | Type of coordinate system used to georeference the image: 'ModelTypeProjected', 'ModelTypeGeographic', 'ModelTypeGeocentric', or ''. |
| PCS | Projected coordinate system |
| Projection | EPSG identifier for the underlying projection method |
| MapSys | Map system, if applicable: 'STATE_PLANE_27', 'STATE_PLANE_83', 'UTM_NORTH', 'UTM_SOUTH', or '' |

| Field | Description |
|--------------|--|
| Zone | double indicating the UTM or State Plane Zone number, empty ([]) if not applicable or unknown |
| CTProjection | GeoTIFF identifier for the underlying projection method |
| ProjParm | N-by-1 double vector containing projection parameter values. The identity of each element is specified by the corresponding element of ProjParmId. Lengths are in meters, angles in decimal degrees. |
| ProjParmId | N-by-1 cell array listing the projection parameter identifier for each corresponding numerical element of ProjParm: <ul style="list-style-type: none"> • 'ProjNatOriginLatGeoKey' • 'ProjNatOriginLongGeoKey' • 'ProjFalseEastingGeoKey' • 'ProjFalseNorthingGeoKey' • 'ProjFalseOriginLatGeoKey' • 'ProjFalseOriginLongGeoKey' • 'ProjCenterLatGeoKey' • 'ProjCenterLongGeoKey' • 'ProjAzimuthAngleGeoKey' • 'ProjRectifiedGridAngleGeoKey' • 'ProjScaleAtNatOriginGeoKey' • 'ProjStdParallel1GeoKey' • 'ProjStdParallel2GeoKey' |
| GCS | Geographic coordinate system |
| Datum | Projection datum type, such as 'North American Datum 1927' or 'North American Datum 1983' |
| Ellipsoid | Ellipsoid name as defined by the ellipsoid.csv EPSG file |
| SemiMajor | double indicating the length of the semimajor axis of the ellipsoid, in meters |
| SemiMinor | double indicating the length of the semiminor axis of the ellipsoid, in meters |

| Field | Description | | | | | | |
|-------------------|--|------------|-------------|-------------|---|-------------|--|
| PM | Prime meridian location, for example, 'Greenwich' or 'Paris' | | | | | | |
| PmLongToGreenwich | double indicating the decimal degrees of longitude between this prime meridian and Greenwich. Prime meridians to the west of Greenwich are negative. | | | | | | |
| UOMLength | Units of length used in the projected coordinate system | | | | | | |
| UOMLengthInMeters | double defining the UOMLength unit in meters. | | | | | | |
| UOMAngle | Angular units used for geographic coordinates | | | | | | |
| UOMAngleInDegrees | double defining the UOMAngle unit in degrees. | | | | | | |
| TiePoints | Structure containing the image tiepoints. The structure contains these fields: | | | | | | |
| | <table border="1"> <thead> <tr> <th>Field Name</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>ImagePoints</td> <td>Structure containing row and column coordinates of each image tiepoint. The ImagePoints structure contains these fields: <ul style="list-style-type: none"> Row — double array of size 1-by-N Col — double array of size 1-by-N </td> </tr> <tr> <td>WorldPoints</td> <td>Structure containing the x and y world coordinates of the tiepoints. The WorldPoints structure contains these fields: <ul style="list-style-type: none"> X — double array of size 1-by-N Y — double array of size 1-by-N </td> </tr> </tbody> </table> | Field Name | Description | ImagePoints | Structure containing row and column coordinates of each image tiepoint. The ImagePoints structure contains these fields: <ul style="list-style-type: none"> Row — double array of size 1-by-N Col — double array of size 1-by-N | WorldPoints | Structure containing the x and y world coordinates of the tiepoints. The WorldPoints structure contains these fields: <ul style="list-style-type: none"> X — double array of size 1-by-N Y — double array of size 1-by-N |
| Field Name | Description | | | | | | |
| ImagePoints | Structure containing row and column coordinates of each image tiepoint. The ImagePoints structure contains these fields: <ul style="list-style-type: none"> Row — double array of size 1-by-N Col — double array of size 1-by-N | | | | | | |
| WorldPoints | Structure containing the x and y world coordinates of the tiepoints. The WorldPoints structure contains these fields: <ul style="list-style-type: none"> X — double array of size 1-by-N Y — double array of size 1-by-N | | | | | | |
| PixelScale | 3-by-1 double array that specifies the X, Y, Z pixel scale values. | | | | | | |

| Field | Description |
|--------------------------|--|
| <code>SpatialRef</code> | <p>Value depends on the value of the <code>ModelType</code> field:</p> <ul style="list-style-type: none">• <code>'ModelTypeProjected'</code> — <code>SpatialRef</code> is a map raster reference object.• <code>'ModelTypeGeographic'</code> — <code>SpatialRef</code> is a geographic raster reference object, unless the geometric transformation is affine, in which case it is <code>''</code> (empty).• <code>'ModelTypeGeocentric'</code> — <code>SpatialRef</code> is <code>''</code> (empty).• <code>''</code> (empty) — <code>geotiffinfo</code> issues a warning and <code>SpatialRef</code> is a map raster reference object. <p>If the spatial referencing is ambiguously defined by the GeoTIFF file, then <code>SpatialRef</code> is <code>''</code> (empty).</p> |
| <code>RefMatrix</code> | <p>3-by-2 double referencing matrix that must be unambiguously defined by the GeoTIFF file. Otherwise it is empty (<code>[]</code>).</p> |
| <code>BoundingBox</code> | <p>2-by-2 double array that specifies the minimum (row 1) and maximum (row 2) values for each dimension of the image data in the GeoTIFF file.</p> |

| Field | Description |
|--------------|---|
| CornerCoords | Structure with six fields that contains coordinates of the outer corners of the GeoTIFF image. Each field is a 1-by-4 double array, or empty ([]) if unknown. The arrays contain the coordinates of the outer corners of the corner pixels, starting from the (1, 1) corner and proceeding clockwise: |
| Field | Description |
| X | Easting coordinates in the projected coordinate system. X equals Lon (below) if <i>ModelType</i> is 'ModelTypeGeographic' |
| Y | Northing coordinates in the projected coordinate system. Y equals Lat (below) if <i>ModelType</i> is 'ModelTypeGeographic' |
| Row | Row coordinates of the corner. |
| Col | Column coordinates of the corner. |
| Lat | Latitudes of the corner. |
| Lon | Longitudes of the corner. |

| Field | Description |
|--------------|--|
| GeoTIFFCodes | <p>Structure containing raw numeric values for those GeoTIFF fields that are encoded numerically in the file. These raw values, converted to a character vectors elsewhere in the <code>info</code> structure, are provided here for reference.</p> <ul style="list-style-type: none">• Model• PCS• GCS• UOMLength• UOMAngle• Datum• PM• Ellipsoid• ProjCode• Projection• CTProjection• ProjParmId• MapSys |

Each is scalar, except for `ProjParmId`, which is a column vector.

| Field | Description | | | | | | | | | | | | | | | | |
|------------------------|---|-------|-------|--------------------|---------------|------------------|---------------|------------------------|----------------|--------------------|------------------|-------------------|------------------|--------------------|---------------|-------------------|--------------------------|
| GeoTIFFTags | Structure containing field names that match the GeoTIFF tags in the file. At least one GeoTIFF tag must be present in the file or an error is issued. The following fields may be included: <table border="1" data-bbox="516 420 1332 760"> <thead> <tr> <th>Field</th> <th>Value</th> </tr> </thead> <tbody> <tr> <td>ModelPixelScaleTag</td> <td>1-by-3 double</td> </tr> <tr> <td>ModelTiepointTag</td> <td>1-by-6 double</td> </tr> <tr> <td>ModelTransformationTag</td> <td>1-by-16 double</td> </tr> <tr> <td>GeoKeyDirectoryTag</td> <td>scalar structure</td> </tr> <tr> <td>GeoAsciiParamsTag</td> <td>character vector</td> </tr> <tr> <td>GeoDoubleParamsTag</td> <td>1-by-N double</td> </tr> <tr> <td>RPCCoefficientTag</td> <td>scalar RPCCoefficientTag</td> </tr> </tbody> </table> <p>The <code>GeoKeyDirectoryTag</code> contains field names that match the names of the "GeoKeys". For more information about the "GeoKeys" refer to the GeoTIFF specification.</p> <p>The <code>RPCCoefficientTag</code> contains properties with names corresponding to the tag elements listed in the RPCs in GeoTIFF technical note at: http://geotiff.maptools.org/rpc_prop.html</p> | Field | Value | ModelPixelScaleTag | 1-by-3 double | ModelTiepointTag | 1-by-6 double | ModelTransformationTag | 1-by-16 double | GeoKeyDirectoryTag | scalar structure | GeoAsciiParamsTag | character vector | GeoDoubleParamsTag | 1-by-N double | RPCCoefficientTag | scalar RPCCoefficientTag |
| Field | Value | | | | | | | | | | | | | | | | |
| ModelPixelScaleTag | 1-by-3 double | | | | | | | | | | | | | | | | |
| ModelTiepointTag | 1-by-6 double | | | | | | | | | | | | | | | | |
| ModelTransformationTag | 1-by-16 double | | | | | | | | | | | | | | | | |
| GeoKeyDirectoryTag | scalar structure | | | | | | | | | | | | | | | | |
| GeoAsciiParamsTag | character vector | | | | | | | | | | | | | | | | |
| GeoDoubleParamsTag | 1-by-N double | | | | | | | | | | | | | | | | |
| RPCCoefficientTag | scalar RPCCoefficientTag | | | | | | | | | | | | | | | | |
| ImageDescription | Description of the image. If no description is included in the file, the field is omitted. | | | | | | | | | | | | | | | | |

See Also

`RPCCoefficientTag` | `geotiffread` | `geotiffwrite` | `projfwd` | `projinv`

Introduced before R2006a

geotiffread

Read GeoTIFF file

Syntax

```
[A,R] = geotiffread(filename)
[X,cmap,R] = geotiffread(filename)
[A,refmat,bbox] = geotiffread(filename)
[X,cmap,refmat,bbox] = geotiffread(filename)
[ ___ ] = geotiffread(filename,idx)
[ ___ ] = geotiffread(url, ___)
```

Description

`[A,R] = geotiffread(filename)` reads a georeferenced grayscale, RGB, or multispectral image or data grid from the GeoTIFF file specified by `filename` into `A` and creates a spatial referencing object, `R`.

`[X,cmap,R] = geotiffread(filename)` reads an indexed image into `X` and the associated colormap into `cmap`, and creates a spatial referencing object, `R`.

`[A,refmat,bbox] = geotiffread(filename)` reads a georeferenced grayscale, RGB, or multispectral image or data grid into `A`, the corresponding referencing matrix into `refmat`, and the bounding box into `bbox`.

`[X,cmap,refmat,bbox] = geotiffread(filename)` reads an indexed image into `X`, the associated colormap into `cmap`, the referencing matrix into `refmat`, and the bounding box into `bbox`. The referencing matrix must be unambiguously defined by the GeoTIFF file, otherwise it and the bounding box are returned empty.

`[___] = geotiffread(filename,idx)` reads one image from a multi-image GeoTIFF file.

`[___] = geotiffread(url, ___)` reads the GeoTIFF image from a URL.

Examples

Read and Display the Boston GeoTIFF Image

```
[boston,R] = geotiffread('boston.tif');  
figure  
mapshow(boston,R);  
axis image off
```



boston.tif copyright © GeoEye™, all rights reserved.

Input Arguments

filename — Name of GeoTIFF file

character vector | string scalar

Name of the GeoTIFF file, specified as a string scalar or character vector. Include the folder name in `filename` or place the file in the current folder or in a folder on the MATLAB path. If the named file includes the extension `.TIF` or `.TIFF` (either upper- or lowercase), you can omit the extension from `filename`.

idx — Index of image in GeoTIFF file

1 (default) | positive integer

Index of image in GeoTIFF file, specified as a positive integer. For example, if `idx` is 3, `geotiffread` reads the third image in the file. By default, `idx` indexes to the first image in the file.

url — Internet URL

character vector | scalar string

Internet URL, specified as a string scalar or character vector. The URL must include the protocol type (e.g., "http://").

Output Arguments

A — Georeferenced image or data grid

M-by-*N* numeric matrix | *M*-by-*N*-by-*P* numeric array

Georeferenced image or data grid, returned as one of the following:

- An *M*-by-*N* numeric matrix when the file contains a grayscale image or data grid
- An *M*-by-*N*-by-*P* numeric array when the file contains a color image, multispectral image, hyperspectral image, or data grid

The class of `A` depends on the storage class of the pixel data in the file, which is related to the `BitsPerSample` property as returned by the `imfinfo` function.

R — Spatial referencing object

geographic raster reference object | map raster reference object

Spatial referencing object, returned as one of the following.

- A geographic raster reference object of type `GeographicCellsReference` or `GeographicPostingsReference`. This object is returned when the image or data grid is referenced to a geographic coordinate system.
- A map raster reference object of type `MapCellsReference` or `MapPostingsReference`. This object is returned when the image or data grid is referenced to a projected coordinate system.

X — Indexed image*M*-by-*N* numeric matrix

Indexed image, returned as an *M*-by-*N* numeric matrix.

cmap — Color map*c*-by-3 numeric matrix

Color map associated with indexed image *X*, specified as an *c*-by-3 numeric matrix. There are *c* colors in the color map, each represented by a red, green, and blue pixel value. Colormap values are rescaled into the range [0,1].

refmat — Referencing matrix

3-by-2 numeric matrix | []

Referencing matrix, returned as 3-by-2 numeric matrix that transforms raster row and column indices to or from geographic coordinates according to:

$$[\text{lon lat}] = [\text{row col 1}] * \text{refmat}$$

refmat defines a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. *refmat* must be unambiguously defined by the GeoTIFF file, otherwise it and the bounding box, *bbox*, are returned empty.

Data Types: double

bbox — Bounding box

2-by-2 numeric matrix | []

Bounding box, returned as a 2-by-2 numeric matrix that specifies the minimum (row 1) and maximum (row 2) values for each dimension of the image data in the GeoTIFF file. *bbox* is returned empty if *refmat* is ambiguously defined by the GeoTIFF file.

Data Types: double

Tips

- `geotiffread` imports pixel data using the TIFF-reading capabilities of the MATLAB function `imread` and likewise shares any limitations of `imread`. Consult the `imread` documentation for information on TIFF image support.

See Also

`geoshow` | `geotiffinfo` | `geotiffwrite` | `imread` | `mapshow`

Introduced before R2006a

geotiffwrite

Write GeoTIFF file

Syntax

```
geotiffwrite(filename,A,R)
geotiffwrite(filename,X,cmap,R)
geotiffwrite( ____,Name,Value)
```

Description

`geotiffwrite(filename,A,R)` writes a georeferenced image or data grid, `A`, spatially referenced by `R`, into an output file, `filename`.

`geotiffwrite(filename,X,cmap,R)` writes the indexed image in `X` and its associated colormap, `cmap`, to `filename`. `X` is spatially referenced by `R`.

`geotiffwrite(____,Name,Value)` writes an image or data grid with one or more `Name,Value` pair arguments that control various characteristics of the output file.

Examples

Write Image from JPEG File to GeoTIFF File

Read JPEG image from file.

```
basename = 'boston_ovr';
imagefile = [basename '.jpg'];
RGB = imread(imagefile);
```

Derive world file name from image file name, read the world file, and construct a spatial referencing object.


```
worldfile = getworldfilename(imagefile);
R = worldfileread(worldfile, 'geographic', size(RGB));
```

Write image data and referencing data to GeoTIFF file.

```
filename = [basename '.tif'];  
geotiffwrite(filename, RGB, R)
```

Construct an empty map axes and display the map.

```
figure  
usamap(RGB, R)  
geoshow(filename)
```



Convert ClassicTIFF GeoTIFF file to Tiled BigTIFF File

Read data from a file in classic TIFF format into the workspace.

```
infilename = 'boston.tif';
[A,R] = geotiffread(infilename);
```

Retrieve the metadata from the file. You pass this into the new BigTIFF version of the file.

```
info = geotiffinfo(infilename);
```

Extract the value of the GeoKeyDirectoryTag field from the info structure returned by geotiffinfo. Set the value of two TIFF tags that specify the length and width of tiles.

```
geoTags = info.GeoTIFFTags.GeoKeyDirectoryTag;
tiffTags = struct('TileLength',1024,'TileWidth',1024);
```

Write the data to a new GeoTIFF file, using the TiffType parameter to specify the file format as 'bigtiff'. Include the geoTags information and the tiffTags in the metadata in the new file.

```
outfilename = 'boston_bigtiff.tif';
geotiffwrite(outfilename,A,R,'GeoKeyDirectoryTag',geoTags, ...
    'TiffType','bigtiff','TiffTags',tiffTags)
```

Write WMS Image to GeoTIFF File

Read data from WMS server.


```
nasaLayers = wmsfind('nasa', 'SearchField', 'serverurl');
layerName = 'bluemarbleng';
layer = refine(nasaLayers, layerName, 'SearchField', 'layername', ...
    'MatchType', 'exact');
[A, R] = wmsread(layer(1));
```

Write data to GeoTIFF file.

```
filename = [layerName '.tif'];
geotiffwrite(filename, A, R)
```

View data in file.

```
figure
worldmap world
geoshow(filename)
```



Write Concord Orthophotos to Single GeoTIFF File

Read the two adjacent orthophotos and combine them.

```
X_west = imread('concord_ortho_w.tif');
X_east = imread('concord_ortho_e.tif');
X = [X_west X_east];
```

Construct referencing objects for the orthophotos and for their combination.


```
R_west = worldfileread('concord_ortho_w.tfw', 'planar', size(X_west));
R_east = worldfileread('concord_ortho_e.tfw', 'planar', size(X_east));
R = R_west;
R.XLimWorld = [R_west.XLimWorld(1) R_east.XLimWorld(2)];
R.RasterSize = size(X);
```

Write the combined image to a GeoTIFF file. Use the code number, 26986, indicating the PCS_NAD83_Massachusetts Projected Coordinate System.

```
coordRefSysCode = 26986;  
filename = 'concord_ortho.tif';  
geotiffwrite(filename, X, R, 'CoordRefSysCode', coordRefSysCode);
```

Display the map.

```
figure  
mapshow(filename)
```



Write Subset of GeoTIFF File to New GeoTIFF File

Read GeoTIFF file.


```
[A, R] = geotiffread('boston.tif');
```

Specify subset of data that you want to write.

```
m = size(A,1);
n = 1024;
firstrow = m-n+1;
lastrow = m;
firstcol = 1;
lastcol = n;
subImage = A(firstrow:lastrow, firstcol:lastcol, :);
xi = [firstcol - .5, lastcol + .5];
yi = [firstrow - .5, lastrow + .5];
[xlimits, ylimits] = intrinsicToWorld(R, xi, yi);
subR = R;
subR.RasterSize = size(subImage);
subR.XLimWorld = sort(xlimits);
subR.YLimWorld = sort(ylimits);
info = geotiffinfo('boston.tif');
```

Write subset to file.

```
filename = 'boston_subimage.tif';
geotiffwrite(filename, subImage, subR, ...
    'GeoKeyDirectoryTag', info.GeoTIFFTags.GeoKeyDirectoryTag);
figure
mapshow(filename);
```



Write SDTS DEM terrain data to GeoTIFF File


This example shows how to write the Mount Washington SDTS DEM terrain data to GeoTIFF. The data are referenced to Universal Transverse Mercator (UTM), Zone 19, in the North American Datum of 1927. This corresponds to the GeoTIFF PCS_NAD27_UTM_zone_19N code number 26719. Set the raster interpretation to 'postings' because the data is USGS DEM. This corresponds to the GeoTIFF raster type `PixellIsPoint`.

Read SDTS DEM data.

```
[Z, refmat] = sdtsemread('9129CATD.ddf');
R = refmatToMapRasterReference(refmat, size(Z), 'postings');
key.GTModelTypeGeoKey = 1; % Projected Coordinate System (PCS)
key.GTRasterTypeGeoKey = 2; % PixelIsPoint
key.ProjectedCSTypeGeoKey = 26719;
filename = '9129.tif';
geotiffwrite(filename, Z, R, 'GeoKeyDirectoryTag', key);
```


Plot the outline of the state of New Hampshire in UTM.

```
S = shaperead('usastatelo', 'UseGeoCoords', true, 'Selector', ...
    {@(name) any(strcmp(name,{'New Hampshire'})), 'Name'});
proj = geotiffinfo(filename);
[x, y] = projfwd(proj, [S.Lat], [S.Lon]);
figure
mapshow(x,y)
```



Display the GeoTIFF DEM file.

```
hold on  
h = mapshow(filename, 'DisplayType', 'surface');  
demcmap(get(h, 'ZData'))
```



Read and Write TIFF File Containing RPC Metadata

This example shows how to read a file containing RPC metadata, modify the file, and then write the file, including the RPC metadata in the new file. To illustrate this process, the example first creates a sample TIFF file containing RPC Metadata.

Create a Sample TIFF File with RPC Metadata

Create a sample test TIFF file containing RPC metadata. For this test file, create a toy image and a referencing object associated with the image.


```
myimage = zeros(180,360);
latlim = [-90 90];
lonlim = [-180 180];
R = georefcells(latlim,lonlim,size(myimage));
```

Create an `RPCCoefficientTag` metadata object and set some fields with typical values. The toolbox uses the `RPCCoefficientTag` object to represent RPC metadata in human readable form.

```
rpctag = map.geotiff.RPCCoefficientTag;
rpctag.LineOffset = 1;
rpctag.SampleOffset = 1;
rpctag.LineScale = 2;
rpctag.SampleScale = 2;
rpctag.GeodeticHeightScale = 500;
```

Write the image, the associated referencing object, and the `RPCCoefficientTag` object to a file.

```
geotiffwrite('myfile',myimage,R,'RPCCoefficientTag',rpctag)
```

Read the Metadata and Image Data from the Sample TIFF File

Read the metadata and the image data from the test file. `geotiffinfo` returns the RPC metadata in the `GeoTIFFTags` field of the structure returned.

```
info = geotiffinfo('myfile');
[imagedata, R] = geotiffread('myfile');
```

Write Modified Image Data and RPC Metadata to File

First modify the image data read from the file. For example, set all the zero-valued pixels to 1 in the image.

```
imagedata(imagedata==0)= 1;
```

Write the modified image to a file, along with the RPC metadata from the original file.

```
geotiffwrite('myfile2',imagedata,R,...
    'RPCCoefficientTag',info.GeoTIFFTags.RPCCoefficientTag)
```

Write Raw RPC Coefficient Metadata to GeoTIFF File

This example shows how to write RPC coefficient metadata to a TIFF file. In a real workflow, you would create the RPC coefficient metadata according to the TIFF extension specification. This example does not show the specifics of how to create valid RPC metadata. To simulate raw RPC metadata, the example creates a sample TIFF file with RPC metadata and then uses `imfinfo` to read this RPC metadata in raw, unprocessed form from the file. The example then writes this raw RPC metadata to a file using the `geotiffwrite` function.

Create Raw RPC Coefficient Metadata

To simulate raw RPC metadata, create a simple test file and write some RPC metadata to the file. For this test file, create a toy image and a referencing object associated with the image.

```
myimage = zeros(180,360);  
latlim = [-90 90];  
lonlim = [-180 180];  
R = georefcells(latlim,lonlim,size(myimage));
```

Create an `RPCCoefficientTag` metadata object and set some of the fields. The toolbox uses the `RPCCoefficientTag` object to represent RPC metadata in human readable form.

```
rpctag = map.geotiff.RPCCoefficientTag;  
rpctag.LineOffset = 1;  
rpctag.SampleOffset = 1;  
rpctag.LineScale = 2;  
rpctag.SampleScale = 2;  
rpctag.GeodeticHeightScale = 500;
```

Write the image, the associated referencing object, and the `RPCCoefficientTag` object to a file.

```
geotiffwrite('myfile',myimage,R,'RPCCoefficientTag',rpctag)
```

Read Raw RPC Coefficient Metadata

Read the RPC coefficient metadata from the test file using the `imfinfo` function. When it encounters unfamiliar metadata, `imfinfo` returns the data, unprocessed, in the `UnknownTags` field. Note how the `UnknownTags` field contains an array of 92 doubles. This is the raw RPC coefficient metadata, read from the file in unprocessed form.

```

info = imfinfo('myfile.tif');
info.UnknownTags

ans = struct with fields:
    ID: 50844
    Offset: 10672
    Value: [1x92 double]

```

Write Raw RPC Metadata to a File

Write the raw RPC metadata to a file. First, extract the RPC coefficient metadata from the info structure.

```
value = info.UnknownTags.Value;
```

Then, construct an RPCCoefficientTag object, passing the raw RPC metadata (array of 92 doubles) as an argument.

```
rpcdata = map.geotiff.RPCCoefficientTag(value)
```

```

rpcdata =
  RPCCoefficientTag with properties:

    BiasErrorInMeters: -1
    RandomErrorInMeters: -1
    LineOffset: 1
    SampleOffset: 1
    GeodeticLatitudeOffset: 0
    GeodeticLongitudeOffset: 0
    GeodeticHeightOffset: 0
    LineScale: 2
    SampleScale: 2
    GeodeticLatitudeScale: 1
    GeodeticLongitudeScale: 1
    GeodeticHeightScale: 500
    LineNumeratorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
    LineDenominatorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
    SampleNumeratorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
    SampleDenominatorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]

```

Pass the RPCCoefficientTag object to the geotiffwrite function and write the RPC metadata to a file.

```
geotiffwrite('myfile2',myimage,R,'RPCCoefficientTag',rpcdata)
```

To verify that the data was written to the file, read the RPC metadata from the TIFF file using `geotiffinfo`. Compare the returned RPC metadata with the metadata written to the test file.

```
ginfo = geotiffinfo('myfile2');
ginfo.GeoTIFFTags.RPCCoefficientTag

ans =
  RPCCoefficientTag with properties:

    BiasErrorInMeters: -1
    RandomErrorInMeters: -1
    LineOffset: 1
    SampleOffset: 1
    GeodeticLatitudeOffset: 0
    GeodeticLongitudeOffset: 0
    GeodeticHeightOffset: 0
    LineScale: 2
    SampleScale: 2
    GeodeticLatitudeScale: 1
    GeodeticLongitudeScale: 1
    GeodeticHeightScale: 500
    LineNumeratorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
    LineDenominatorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
    SampleNumeratorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
    SampleDenominatorCoefficients: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
```

Input Arguments

filename — Name and location of output file

character vector | string scalar

Name and location of output file, specified as a string scalar or character vector. If your filename includes an extension, it must be `'.tif'` or `'.TIF'`. If the input, `A`, is at least 160-by-160 in size, the output file is a tiled GeoTIFF file. Otherwise, `geotiffwrite` organizes the output file as rows-per-strip.

Data Types: `char` | `string`

A — Georeferenced image or data grid

M -by- N numeric matrix | M -by- N -by- P numeric array

Georeferenced image or data grid, specified as one of the following:

- An M -by- N numeric matrix representing a grayscale image or data grid
- An M -by- N -by- P numeric array representing a color image, multispectral image, hyperspectral image, or data grid

The coordinates of `A` are geographic and in the 'WGS 84' coordinate system, unless you specify 'GeoKeyDirectoryTag' or 'CoordRefSysCode' and indicate a different coordinate system.

Data Types: `double` | `single` | `uint8` | `uint16` | `uint32` | `uint64` | `int8` | `int16` | `int32` | `int64` | `logical`

R — Spatial referencing information

geographic raster reference object | map raster reference object | referencing matrix | referencing vector

Spatial referencing information, specified as a geographic raster reference object of type `GeographicCellsReference` or `GeographicPostingsReference`, a map raster reference object of type `MapCellsReference` or `MapPostingsReference`, a referencing matrix, or a referencing vector.

If you are working with image coordinates in a projected coordinate system and `R` is a map raster reference object or a referencing matrix, specify 'GeoKeyDirectoryTag' or 'CoordRefSysCode' accordingly.

X — Indexed image

M -by- N numeric matrix

Indexed image data, specified as an M -by- N numeric matrix.

Data Types: `uint8` | `uint16`

cmap — Color map

c -by-3 numeric matrix

Color map associated with indexed image `X`, specified as an c -by-3 numeric matrix. There are c colors in the color map, each represented by a red, green, and blue pixel value.

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single

quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, . . . , NameN, ValueN`.

Example: `'CoordRefSysCode', 26986`

CoordRefSysCode — Coordinate reference system code

4326 (default) | positive integer | string scalar | character vector

Coordinate reference system code for the coordinates of the data, specified as the comma-separated pair consisting of `'CoordRefSysCode'` and a positive integer, string scalar, or character vector. You can specify coordinates in either a geographic or a projected coordinate system. If you specify the coordinate system with a string scalar or character vector, include the `'EPSG: '` prefix. See “Tips” on page 1-619 for a link to the GeoTiff Specification or the EPSG data files (`pcs.csv` and `gcs.csv`) for the code numbers.

If you specify both the `GeoKeyDirectoryTag` and the `CoordRefSysCode`, the coordinate system code in `CoordRefSysCode` takes precedence over the coordinate system key found in the `GeoKeyDirectoryTag`. If one value specifies a geographic coordinate system and the other value specifies a projected coordinate system, you receive an error.

If you do not specify a value for this argument, the default value is 4326, indicating that the coordinates are geographic and in the `'WGS 84'` geographic coordinate system.

Example: `26986`

Example: `'EPSG:26986'`

GeoKeyDirectoryTag — GeoKey directory tag

structure

GeoKey directory tag, specified as the comma-separated pair consisting of `'GeoKeyDirectoryTag'` and a structure that specifies the GeoTIFF coordinate reference system and meta-information. The structure contains field names that match the GeoKey names in the GeoTIFF specification. The field names are case insensitive. The structure can be obtained from the GeoTIFF information structure, returned by `geotiffinfo`, in the field, `GeoTIFFTags.GeoKeyDirectoryTag`.

if you specify the `GTRasterTypeGeoKey` field, `geotiffwrite` ignores it. The value for this GeoKey is derived from `R`. If you set certain fields of the `GeoKeyDirectoryTag` to inconsistent settings, you receive an error message. For instance, if `R` is a geographic raster reference object or a `refvec`, and you specify a `ProjectedCSTypeGeoKey` field or

you set the `GTModelTypeGeoKey` field to 1 (projected coordinate system), you receive an error. Likewise, if `R` is a map raster reference object and you do not specify a `ProjectedCSTypeGeoKey` field or a `CoordRefSysCode`, or the `GTModelTypeGeoKey` field is set to 2 (geographic coordinate system), you receive an error message.

RPCCoefficientTag — Rational Polynomial Coefficients (RPC) tag

RPCCoefficientTag object

Values for the optional RPC TIFF tag, specified as the comma-separated pair consisting of 'RPCCoefficientTag' and an RPCCoefficientTag object.

TiffTags — TIFF tags

structure

Values for the TIFF tags in the output file, specified as the comma-separated pair consisting of 'TiffTags' and a structure. The field names of the structure match the TIFF tag names supported by the Tiff class. The field names are case insensitive.

You cannot set most TIFF tags using the structure input.

TiffTags Exceptions

0
1
2
3
4
5
6
7
8
9
10
11
12
13
14
15
16
17
18
19
20
21
22
23
24
25
26
27
28
29
30
31
32
33
34
35
36
37
38
39
40
41
42
43
44
45
46
47
48
49
50
51
52
53
54
55
56
57
58
59
60
61
62
63
64
65
66
67
68
69
70
71
72
73
74
75
76
77
78
79
80
81
82
83
84
85
86
87
88
89
90
91
92
93
94
95
96
97
98
99

The function sets several TIFF tags. The field names corresponding to the TIFF tag, their corresponding field values set by the function, their permissible values (if different from the Tiff class), and their data type are noted in the following table.

Automatic TIFF Tags

| Field Name | Description |
|---------------------------|---|
| Compression | Type of image compression. The default is 'PackBits'. Other permissible values are 'LZW', 'Deflate', and 'none'. Numeric values, <code>Tiff.Compression.LZW</code> , <code>Tiff.Compression.PackBits</code> , <code>Tiff.Compression.Deflate</code> , or <code>Tiff.Compression.None</code> can also be used. |
| PhotometricInterpretation | Type of photometric interpretation. The field name can be shortened to <code>Photometric</code> . The value is set based on the input image characteristic, using the following algorithm: If A is [M-by-N-by-3] and is class type <code>uint8</code> or <code>uint16</code> , then the value is 'RGB'. For all other sizes and data types, the value is 'MinIsBlack'. If the X, CMAP syntax is supplied, the value is 'Palette'. If the value is set to 'RGB' and A is not [M-by-N-by-3], an error is issued. Permissible values are 'MinIsBlack', 'RGB', 'Palette', 'Separated'. The numeric values, <code>Tiff.Photometric.MinIsBlack</code> , <code>Tiff.Photometric.RGB</code> , <code>Tiff.Photometric.Palette</code> , <code>Tiff.Photometric.Separated</code> can also be used. |
| Software | Software maker of the file. The value is set to the value 'MATLAB, Mapping Toolbox, The MathWorks, Inc.'. To remove the value, set the tag to the empty string or character vector (''). |
| RowsPerStrip | A scalar positive integer-valued number specifying the desired rows per strip in the output file. If the size of A is less than [160-by-160], <code>geotiffwrite</code> sets <code>RowsPerStrip</code> to 1. If you specify <code>RowsPerStrip</code> and <code>TileWidth</code> , with or without <code>TileLength</code> , <code>geotiffwrite</code> issues an error. |

| Field Name | Description |
|------------|---|
| TileWidth | A scalar positive integer-valued number and a multiple of 16 specifying the width of the tiles. TileWidth is set if the size of A is greater than [160-by-160]. If so, the value is such that a maximum of [10-by-10] tiles are created. If you specify both RowsPerStrip and TileWidth, geotiffwrite issues an error. |
| TileLength | A scalar positive integer-valued number and a multiple of 16 specifying the length of the tiles. TileLength is set if the size of A is greater than [160-by-160]. If so, the value is such that a maximum of [10-by-10] tiles are created. If you specify both RowsPerStrip and TileLength, geotiffwrite issues an error. |

TiffType — Type of TIFF file

'classictiff' (default) | 'bigtiff'

Type of TIFF file, specified as the comma-separated pair consisting of 'TiffType' and either 'classictiff' or 'bigtiff'. The 'classictiff' value creates a Classic TIFF file. The 'bigtiff' value creates a BigTIFF file. In BigTIFF format, files can be larger than 4 GB.

While using the 'bigtiff' format enables you to create files larger than 4 GB, the data you want to write must fit in memory.

Tips

- If you are working with image coordinates in a projected coordinate system and R is a map raster reference object or a referencing matrix, set the GeoKeyDirectoryTag or CoordRefSysCode argument, accordingly.
- Check the GeoTIFF specification for values of the following parameters:
 - 'CoordRefSysCode' value for geographic coordinate systems
 - 'CoordRefSysCode' value for projected coordinate systems
 - GeoKey field names for the 'GeoKeyDirectoryTag'

You can also obtain the 'CoordRefSysCode' values from the EPSG data files (pcs.csv and gcs.csv) in the folder:

matlabroot/toolbox/map/mapproj/projdata/epsg_csv

See Also

[RPCCoefficientTag](#) | [Tiff](#) | [geotiffinfo](#) | [geotiffread](#) | [imread](#) | [imwrite](#)

Introduced before R2006a

getCapabilities

Get capabilities document from server

Syntax

```
capabilities = getCapabilities(server)
```

Description

`capabilities = getCapabilities(server)` retrieves the capabilities document from the Web map service server, `server`, and updates the `RequestURL` property of the `server`.

Examples

Retrieve the Capabilities Document from the NASA SVS Image Server

```
nasa = wmsfind('NASA SVS Image', 'SearchField', 'servertitle');  
serverURL = nasa(1).ServerURL;  
server = WebMapServer(serverURL);  
capabilities = getCapabilities(server);
```

Input Arguments

server — Web map server

WebMapServer object

Web map server, specified as a WebMapServer object.

Output Arguments

capabilities — Capabilities document

WMSCapabilities object

Capabilities document, returned as a WMSCapabilities object.

Tips

The `getCapabilities` method accesses the Internet to retrieve the document. Periodically, the WMS server is unavailable. Retrieving the document can take several minutes.

See Also

WMSCapabilities | WebMapServer | disp

Introduced before R2006a

getm

Map object properties

Syntax

```
mat = getm(h)
mat = getm(h,MapPropertyName)
getm('MapProjection')
getm('axes')
getm('units')
```

Description

`mat = getm(h)` returns the map structure of the map axes specified by its handle. If the handle of a child of the map axes is specified, only its properties are returned.

`mat = getm(h,MapPropertyName)` returns the specified property value.

`getm('MapProjection')` lists all available projections.

`getm('axes')` lists the map axes properties by property name.

`getm('units')` lists the available units.

Examples

Create a default map axes and query a property value:

```
axesm('mercator','AngleUnits','degrees')
getm(gca,'MapParallels')
```

```
ans =
     0
```

See Also

axesm | setm

Introduced before R2006a

getMap

Get raster map from server

Syntax

```
A = getMap(server, mapRequestURL)
```

Description

A = getMap(server, mapRequestURL) dynamically renders and retrieves a color or grayscale, geographically referenced, raster map from the Web map services server, server, and stores it in A. Parameters in the URL, mapRequestURL, define the map. The getMap function also updates the RequestURL property of the server with mapRequestURL.

Examples

Retrieve Map from NASA Earth Observations WMS Server


Retrieve a map of the Blue Marble global mosaic layer from the NASA Earth Observations WMS server.

```
neowms = wmsfind('neowms', 'SearchField', 'serverurl');  
layer = refine(neowms, 'bluemarbleng', 'MatchType', 'exact');  
  
server = WebMapServer(layer.ServerURL);  
mapRequest = WMSMapRequest(layer, server);  
A = getMap(server, mapRequest.RequestURL);  
R = mapRequest.RasterReference;
```

Display the map.

```
figure  
worldmap world
```

```
geoshow(A, R)
setm(gca, 'MLabelParallel', -90, 'MLabelLocation', 90)
title(layer.LayerTitle)
```



Courtesy NASA Earth Observing System

Input Arguments

server — Web map server

WebMapServer object

Web map server, specified as a WebMapServer object.

mapRequestURL — URL

character vector

URL, specified as a character vector. Parameters in the URL define the map.

Output Arguments

A — Rendered map

color or grayscale image

Rendered map, returned as a color or grayscale image.

Tips

getMap accesses the Internet to retrieve the map. Periodically, the WMS server is unavailable. Retrieving the map can take several minutes.

See Also

WMSMapRequest | WebMapServer

Introduced before R2006a

getseeds

Interactively assign seeds for data grid encoding

Note `getseeds` will be removed in a future release.

Syntax

```
[row,col,val] = getseeds(map,R,nseeds)
[row,col,val] = getseeds(map,R,nseeds,seedval)
mat = getseeds(...)
```

Description

`[row,col,val] = getseeds(map,R,nseeds)` allows user to identify geographical objects while customizing a raster map. It prompts the user for mouse click positions of objects and assigns them a code value. The user is prompted for the value to seed at each location. The outputs are the row and column of the seed location and the value assigned at that location. `R` is either a 1-by-3 vector containing elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

or a 3-by-2 referencing matrix that transforms raster row and column indices to/from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If `R` is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel.

`[row,col,val] = getseeds(map,R,nseeds,seedval)` assigns the value `seedval` to each location supplied. If `seedval` is a scalar then the same value is assigned at each location. Otherwise, if `seedval` is a vector it must be `length(nseeds)` and each entry is assigned to the corresponding location. `getseeds` operates on the current axes (`gca`).

`mat = getseeds(...)` returns a single output matrix where `mat = [row col val]`.

Examples

Demonstrate this for yourself by typing the following and interactively selecting points:

```
load topo
axesm('gortho','grid','on')
seedmat = getseeds(topo,topolegend,3)
```

When you have selected three points, you are prompted for their values. The regular data grid need not be displayed to execute `getseeds` on it.

See Also

`encodem`

Introduced before R2006a

getworldfilename

Derive worldfile name from image filename

Syntax

```
worldfilename = getworldfilename(imagefilename)
```

Description

`worldfilename = getworldfilename(imagefilename)` returns the name of the corresponding worldfile derived from the name of an image file.

The worldfile and the image file have the same base name. If `imagefilename` follows the “.3” convention, then you create the worldfile extension by removing the middle letter and appending the letter 'w'.

If `imagefilename` has an extension that does not follow the “.3” convention, then a 'w' is appended to the full image name to construct the worldfile name.

If `imagefilename` has no extension, then '.wld' is appended to construct a worldfile name.

Examples

Given the following image filenames, `worldfilename` would return these worldfile names:

| Image File Name | Worldfile Name |
|-----------------|----------------|
| myimage.tif | myimage.tfw |
| myimage.jpeg | myimage.jpegw |
| myimage | myimage.wld |

See Also

mapshow | mapview | worldfileread | worldfilewrite

Introduced before R2006a

globedem

Read Global Land One-km Base Elevation (GLOBE) data

Syntax

```
[Z,refvec] = globedem(filename,scalefactor)
[Z,refvec] = globedem(filename,scalefactor,latlim,lonlim)
[Z,refvec] = globedem(foldername,scalefactor,latlim,lonlim)
```

Description

`[Z,refvec] = globedem(filename,scalefactor)` reads the GLOBE DEM files and returns the result as a regular data grid. The `filename` is given as a string scalar or character vector that does not include an extension. `globedem` first reads the ESRI header file found in the subfolder `'/esri/hdr/'` and then the binary data file `filename`. If the files are not found on the MATLAB path, they can be selected interactively. `scalefactor` is an integer that when equal to 1 gives the data at its full resolution. When `scalefactor` is an integer `n` larger than 1, every `n`th point is returned. The map data is returned as an array of elevations and associated three-element referencing vector. Elevations are given in meters above mean sea level, using WGS 84 as a horizontal datum.

`[Z,refvec] = globedem(filename,scalefactor,latlim,lonlim)` allows a subset of the map data to be read. The limits of the desired data are specified as vectors of latitude and longitude in degrees. The elements of `latlim` and `lonlim` must be in ascending order.

`[Z,refvec] = globedem(foldername,scalefactor,latlim,lonlim)` reads and concatenates data from multiple files within a GLOBE folder tree. The `foldername` input is a string scalar or character vector with the name of the folder that contains both the uncompressed data files and the ESRI header files.

Background

GLOBE, the Global Land One-km Base Elevation data, was compiled by the National Geophysical Data Center from more than 10 different sources of gridded elevation data. GLOBE can be considered a higher resolution successor to TerrainBase. The data set consists of 16 tiles, each covering 50 by 90 degrees. Tiles require as much as 60 MB of storage. Uncompressed tiles take between 100 and 130 MB.

Examples

Determine the file that contains the area around Cape Cod. (This example assumes you have already downloaded some GLOBE data tiles.)

```
latlim = [41 42.5]; lonlim = [-73 -69.9];
globedems(latlim,lonlim)
```

```
ans =
    'f10g'
```

Extract every 20th point from the tile covering the northeastern United States and eastern Canada. If you specify an empty file name (' '), `globedem` presents a file browser that you use to first select the header file and then select the data file interactively.

```
[Z,refvec] = globedem(' ',20);
size(Z)
```

```
ans =
    300    540
```

Extract a subset of the data for Massachusetts at the full resolution.

```
latlim = [41 42.5]; lonlim = [-73 -69.9];
[Z,refvec] = globedem('f10g',1,latlim,lonlim);
size(Z)
```

```
ans =
    181    373
```

Replace the NaNs in the ocean with -1 to color them blue.

```
Z(isnan(Z)) = -1;
```

Extract some data for southern Louisiana in an area that straddles two tiles. Provide the name of the folder containing the data files, and let `globedem` determine which files are required, read from the files, and concatenate the data into a single regular data grid.

```
latlim =[28.61 31.31]; lonlim = [-91.24 -88.62];
globedems(latlim,lonlim)

ans =
    'e10g'
    'f10g'

[Z,refvec] =
globedem('d:\externalData\globe\elev',1,latlim,lonlim);
size(Z)

ans =
    325.00    315.00
```

Tips

The `globedem` function reads data from GLOBE Version 1.0. The data is for elevations only. Elevations are given in meters above mean sea level using WGS 84 as a horizontal datum. Areas with no data, such as the oceans, are coded with NaNs.

The data set and documentation are available over the Internet.

Note For details on locating map data for download over the Internet, see the following documentation at the MathWorks Web site: “Find Geospatial Data Online”.

References

See Web site for the National Oceanic and Atmospheric Administration, National Geophysical Data Center

See Also

`demdataui` | `dted` | `gtopo30` | `satbath` | `tbase` | `usgsdem`

Introduced before R2006a

globedems

GLOBE data filenames for latitude-longitude quadrangle

Syntax

```
tileNames = globedems(latlim,lonlim)
tileNames = globedems(lat,lon)
```

Description

`tileNames = globedems(latlim,lonlim)` returns a cell array of the tile names covering the geographic region for GLOBEDEM digital elevation maps. The region is specified by two-element vectors of latitude and longitude limits in units of degrees.

`tileNames = globedems(lat,lon)` returns a cell array of the tile names covering the geographic region for GLOBEDEM digital elevation maps. The region is specified by scalar latitude and longitude points, in units of degrees.

Background

GLOBE, the Global Land One-km Base Elevation data, was compiled by the National Geophysical Data Center from more than 10 different sources of gridded elevation data. The data set consists of 16 tiles, each covering 50 by 90 degrees. Determining which tiles are needed to cover a particular region generally requires consulting an index map. This function takes the place of such a reference by returning the file names for a given geographic region.

Examples

Which tiles are needed for southern Louisiana?

```
latlim =[28.61 31.31];
lonlim = [-91.24 -88.62];
```

```
globedems(latlim,lonlim)
```

```
ans =  
    'e10g'  
    'f10g'
```

Tips

The `globedems` function reads data from the format GLOBE Version 1.0. `globedem` first reads the corresponding ESRI header file found in the subdirectory `'/esri/hdr/'` and then the binary data file (with no extension).

See Also

`globedem`

Introduced before R2006a

gpxread

Read GPX file

Syntax

`P = gpxread(filename)`

`P = gpxread(URL)`

`S = gpxread(____, 'Index', V)`

`____ = gpxread(____, Name, Value)`

Description

`P = gpxread(filename)` reads point data from the GPS Exchange Format (GPX) file, `filename`, and returns an n -by-1 geopoint vector, `P`, where n is the number of waypoints, or points that define a route or track.

`gpxread` searches the file first for waypoints, then routes, and then tracks, and it returns the first type of data it finds. The `Metadata` field of `P` identifies the feature type ('waypoint', 'track', or 'route') and any additional metadata associated with waypoint, route, or track. If the file contains multiple tracks or routes, `P` contains the points that define the first track or route in the file. If `gpxread` cannot find any features in the file, it returns an empty geopoint vector.

`P = gpxread(URL)` reads the GPX data from a URL. The URL must include the protocol type (for example, `http://`).

`S = gpxread(____, 'Index', V)` returns data from the GPX file in a geoshape vector, rather than a geopoint vector, only if the file contains track or route data and you specify the value of 'Index' as a vector, `V`. Use this syntax when you want to work with the data as a line, rather than as a collection of points.

`____ = gpxread(____, Name, Value)` reads data from a GPX file with additional options, specified by one or more `Name, Value` pair arguments, that control various characteristics of the import. `Name` is the argument name and `Value` is the corresponding

value. Name must appear inside single quotes (' ') and is case insensitive. You can specify several name-value pair arguments in any order.

Examples

Read Waypoints and Display Them Over Image

Read and display waypoints from the `boston_placenames.gpx` file and overlay the points onto the `boston.tif` image.

Read waypoints from a GPX file.

```
p = gpxread('boston_placenames');
```

Read the image file.


```
[A,R] = geotiffread('boston');
```

Convert the length unit of the *X* and *Y* limits to meters for use with the projection structure.

```
proj = geotiffinfo('boston');  
mstruct = geotiff2mstruct(proj);  
R.XWorldLimits = R.XWorldLimits * proj.UOMLengthInMeters;  
R.YWorldLimits = R.YWorldLimits * proj.UOMLengthInMeters;
```


Display the map.

```
figure;  
axesm(mstruct)  
mapshow(A,R);
```



Display the names and positions of each point, overlaid over the image.

```
for k=1:length(p)
    textm(p(k).Latitude, p(k).Longitude, p(k).Name, ...
          'Color',[0 0 0], 'BackgroundColor',[0.9 0.9 0],...
          'Interpreter','none');
end
geoshow(p);
xlim(R.XWorldLimits)
ylim(R.YWorldLimits)
```



Read and Display a Route

Read and display a route from Boston Logan International Airport to Mathworks in Natick, MA.

Read the route information from the GPX file.


```
route = gpxread('sample_route');
```

Compute `latlim` and `lonlim` with a 0.05 buffer.

```
[latlim, lonlim] = geoquadline(route.Latitude, route.Longitude);  
[latlim, lonlim] = bufgeoquad(latlim, lonlim, .05, .05);
```

Display the route.

```
fig = figure;  
pos = fig.Position;  
fig.Position = [300 300 1.25*pos(3) 1.25*pos(4)];  
ax = usamap(latlim, lonlim);  
setm(ax, 'MLabelParallel', 43.5)  
geoshow(route.Latitude, route.Longitude)
```




Extract the elements of route that include descriptions of turns, mark and color code each turn on the map, and construct a legend that displays the descriptions. Reverse the order, so that the legend displays the first turn at the top and the last at the bottom.

```
turns = route(~cellfun(@isempty, route.Description));
turns = turns(end:-1:1);
n = length(turns);
colors = cool(n);
for k=1:n
    geoshow(turns(k).Latitude, turns(k).Longitude, ...
            'DisplayType','point','MarkerEdgeColor',colors(k,:),...
            'Tag','turn','DisplayName',turns(k).Description)
end
legend(findobj(ax,'Tag','turn'),'Location','SouthOutside')
```




```
webmap('openstreetmap')
colors = {'cyan', 'red'};
wmline(tracks, 'Color', colors)
```



Zoom the webmap to view the first track near the MathWorks campus in Natick.

1 Functions — Alphabetical List

```
[latlim, lonlim] = geoquadline(tracks(1).Latitude, tracks(1).Longitude);  
wmlimits(latlim, lonlim)
```




Read and Display Waypoints and Track Log on a Webmap

Read waypoints and track log from the `sample_mixed.gpx` file.

```
wpt = gpxread('sample_mixed');  
trk = gpxread('sample_mixed', 'FeatureType', 'track');
```


Display the waypoints and the track log on a webmap.

```
webmap('worldimagery')  
wmline(trk, 'OverlayName', 'Track Logs');
```



Add web markers to mark the positions of each way point.

```
wmmarker(wpt, 'FeatureName', wpt.Name, 'OverlayName', 'Waypoints')
```

Display Elevation and Time-Area Maps

This example shows how to display elevation and time area maps and calculate distance using track logs.

Read the track log from the `sample_mixed.gpx` file.


```
trk = gpxread('sample_mixed', 'FeatureType', 'track');
```

Convert the time value strings to serial date numbers using `datenum`, and then compute the time-of-day in hours-minutes-seconds.

```
timeStr = strrep(trk.Time, 'T', ' ');  
timeStr = strrep(timeStr, '.000Z', '');  
trk.DateNumber = datenum(timeStr, 31);  
day = fix(trk.DateNumber(1));  
trk.TimeOfDay = trk.DateNumber - day;
```

Display an area plot of the elevation and time values.

```
figure  
area(trk.TimeOfDay, trk.Elevation)  
datetick('x', 13, 'kepticks', 'keplimits')  
ylabel('elevation (meters)')  
xlabel('time(Z) hours:minutes:seconds')  
title({'Elevation Area Plot', datestr(day)});
```




Calculate and display ground track distance. Convert distance in meters to distance in U.S. survey miles.

```
e = wgs84Ellipsoid;
lat = trk.Latitude;
lon = trk.Longitude;
d = distance(lat(1:end-1), lon(1:end-1), lat(2:end), lon(2:end), e);
d = d * unitsratio('sm', 'meter');
```

Display the cumulative ground track distance and elapsed time.

```
trk.ElapsedTime = trk.TimeOfDay - trk.TimeOfDay(1);
figure
line(trk.ElapsedTime(2:end), cumsum(d))
```

```
datetick('x', 13)
ylabel('cumulative ground track distance (statute mile)')
xlabel('elapsed time (hours:minutes:seconds)')
title({'Cumulative Ground Track Distance in Miles', datestr(day), ...
      ['Total Distance in Miles: ' num2str(sum(d))]});
```



Input Arguments

filename — Name of GPX file to open
character vector | string scalar

Name of GPX file to open, specified as a string scalar or character vector. If the file is not in the current folder or in a folder on the MATLAB path, you must specify the folder path. If the file name includes the extension `'.gpx'` (either uppercase or lowercase), you can omit the extension from `filename`.

Example: `'boston_placenames'`

Data Types: `char` | `string`

URL — Internet location containing GPX data

Uniform Resource Locator (URL)

Internet location containing GPX data, specified as a Uniform Resource Locator (URL). The URL must include protocol type (for example, `http://`).

Data Types: `char` | `string`

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (`' '`). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

Example: `'FeatureType', 'track'`

FeatureType — Type of feature to read from file

`'auto'` (default) | `'track'` | `'route'` | `'waypoint'`

Type of feature to read from file, specified as one of the following: `'track'`, `'route'`, `'waypoint'`, or `'auto'`. If `gpxread` cannot find the specified feature in the file, it returns an empty geoint vector.

Example: `'FeatureType', 'waypoint'`

Data Types: `char` | `string`

Index — Index of waypoint, track, or route data in file

scalar or vector of positive integers

Index of waypoint, track, or route data in file, specified as a scalar or vector of positive integers.

- If the value is a scalar, `gpxread` returns the specified waypoint, route, or track as a geopoint vector. If the scalar value is greater than the total number of elements found in the file, `gpxread` returns an empty geopoint vector.
- If the value is a vector, and the file contains waypoints, `gpxread` returns those waypoints specified by the vector. If the file contains routes or tracks (and does not contain waypoints), `gpxread` returns the specified routes or track logs in a geoshape vector. `gpxread` sets the Geometry field of the geoshape vector to 'line'.

Example: 'Index', [1:2] would read up to two routes or tracks, if the file contained routes or tracks, in a geoshape vector.

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64

Output Arguments

P — Waypoint, track, or route data

n-by-1 geopoint vector

Waypoint, track, or route data, returned as an *n*-by-1 geopoint vector, where *n* is the number of points.

For a track log or route with multiple segments, `gpxread` concatenates the coordinates of the segments with NaN separators. NaN denotes numeric elements not found in the file. The empty character vector ('') is used to denote text elements not found in the file.

S — Track or route data

n-by-1 geoshape vector

Track or route data, returned as an *n*-by-1 geopoint vector

Definitions

waypoint

A point of interest, or named feature on a map.

track

An ordered list of waypoints that describe a path.

route

An ordered list of waypoints representing a series of turn points leading to a destination.

Tips

- Excluding extensions, GPX version 1.1 is fully supported. If any other version is detected, a warning is issued. However, in most cases, version 1.0 GPX files can be read successfully unless they contain certain metadata tags. For more information, see the GPX 1.1 Schema Documentation.

See Also

geopoint | geoshape | shaperead

Introduced in R2012a

gradientm

Calculate gradient, slope, and aspect of data grid

Syntax

```
[ASPECT, SLOPE, gradN, gradE] = gradientm(Z, R)
[...] = gradientm(lat, lon, Z)
[...] = gradientm(..., ellipsoid)
[...] = gradientm(lat, lon, Z, ellipsoid, units)
```

Description

[ASPECT, SLOPE, gradN, gradE] = gradientm(Z, R) computes the slope, aspect, and north and east components of the gradient for a regular data grid Z with respect to reference R. If the grid contains elevations in meters, the resulting aspect and slope are in units of degrees clockwise from north and up from the horizontal. The north and east gradient components are the change in the map variable per meter of distance in the north and east directions. The computation uses finite differences for the map variable on the default earth ellipsoid.

R can be a geographic raster reference object, a referencing vector, or a referencing matrix.

If R is a geographic raster reference object, its RasterSize property must be consistent with size(Z).

If R is a referencing vector, it must be a 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If R is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to or from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If R is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a

parallel. Nearest-neighbor interpolation is used by default. NaN is returned for points outside the grid limits or for which `lat` or `lon` contain NaN. All angles are in units of degrees.

`[...] = gradientm(lat, lon, Z)` does the computation for a geolocated data grid. `lat` and `lon`, the latitudes and longitudes of the geolocation points, are in degrees.

`[...] = gradientm(..., ellipsoid)` uses the reference ellipsoid specified by the input `ellipsoid`, which can be a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. If the map contains elevations in the same units of length as the semimajor axis of the ellipsoid, the slope and aspect are in units of degrees. This calling form is most useful for computations on bodies other than the earth.


`[...] = gradientm(lat, lon, Z, ellipsoid, units)` specifies the angle units of the latitude and longitude inputs. The default value is `'degrees'`. For elevation maps in the same units as `ellipsoid(1)`, the resulting slope and aspect are in the specified units. The components of the gradient are the change in the map variable per unit of length, using the same length unit as the semimajor axis of the ellipsoid.

Examples

Calculate Slope of Elevation Data

Compute and display the slope for the 30 arc-second (10 km) Korea elevation data. Slopes in the Sea of Japan are up to 12 degrees at this grid resolution.

```
load korea
[aspect,slope,gradN,gradE] = gradientm(map,refvec);
worldmap(slope,refvec)
geoshow(slope,refvec,'DisplayType','texturemap')
cmap = cool(10);
demcmap('inc',slope,1,[],cmap)
colorbar
latlim = getm(gca,'maplatlimit');
lonlim = getm(gca,'maplonlimit');
land = shaperead('landareas',...
    'UseGeoCoords',true,'BoundingBox',[lonlim latlim]);
geoshow(land,'FaceColor','none')
```



```
set(gca, 'Visible', 'off')
```

Tips

Coarse digital elevation models can considerably underestimate the local slope. For the preceding map, the elevation points are separated by about 10 kilometers. The terrain between two adjacent points is modeled as a linear variation, while actual terrain can vary much more abruptly over such a distance.

See Also

viewshed

Topics

“Geolocated Data Grids”

Introduced before R2006a

grepfields

Identify matching fields in fixed record length files

Note `grepfields` will be removed in a future release. Use `textscan` instead.

Syntax

```
grepfields(filename,searchstring)
grepfields(filename,searchstring,casesens)
grepfields(filename,searchstring,casesens,startcol)
grepfields(filename,searchstring,casesens,startfield,fields)
grepfields(filename,searchstring,casesens,startfield,fields,
machineformat)
indx = grepfields(...)
```

Description

`grepfields(filename,searchstring)` displays lines in the file that begin with the search character vector. The file must have fixed-length records with line endings.

`grepfields(filename,searchstring,casesens)`, with `casesens` 'matchcase', specifies a case-sensitive search. If omitted or 'none', the search character vector matches regardless of the case.

`grepfields(filename,searchstring,casesens,startcol)` searches starting with the specified column. `startcol` is an integer between 1 and the bytes per record in the file. In this calling form, the file is regarded as a text file with line endings.

`grepfields(filename,searchstring,casesens,startfield,fields)` searches within the specified field. `startfield` is an integer between 1 and the number of fields per record. The format of the file is described by the `fields` structure. See `readfields` for recognized fields structure entries. In this calling form, the file can be binary and lack line endings. The search is within `startfield`, which must be a character field.

`grepfields(filename, searchstring, casesens, startfield, fields, machineformat)` opens the file with the specified machine format. `machineformat` must be recognized by `fopen`.

`indx = grepfields(...)` returns the record numbers of matched records instead of displaying them on screen.

Examples

Write a binary file and read it:

```
fid = fopen('testbin','wb');
for i = 1:3
    fwrite(fid,['character' num2str(i) ],'char');
    fwrite(fid,i,'int8');
    fwrite(fid,[i i],'int16');
    fwrite(fid,i,'integer*4');
    fwrite(fid,i,'real*8');
end
fclose(fid);

fs(1).length = 10;fs(1).type = 'char';fs(1).name = 'field 1';
fs(2).length = 1;fs(2).type = 'int8';fs(2).name = 'field 2';
fs(3).length = 2;fs(3).type = 'int16';fs(3).name = 'field 3';
fs(4).length = 1;fs(4).type = 'integer*4';fs(4).name = 'field 4';
fs(5).length = 1;fs(5).type = 'float64';fs(5).name = 'field 5';
```

Find the record matching the character vector 'character2'. The record contains binary data, which cannot be properly displayed.

```
grepfields('testbin','character2','none',1,fs)
character2? ? ? ?@

indx = grepfields('testbin','character2','none',1,fs)
indx =
    2
```

Read the formatted file containing the following:

```
-----
character data 1 1 2 3 1e6 10D6

character data 2 11 22 33 2e6 20D6
```

```
character data 3111222333 3e6 30D6
-----
fs(1).length = 16;fs(1).type = 'char';fs(1).name = 'field 1';
fs(2).length = 3;fs(2).type = '%3d';fs(2).name = 'field 2';
fs(3).length = 1;fs(3).type = '%4g';fs(3).name = 'field 3';
fs(4).length = 1;fs(4).type = '%5D';    fs(4).name = 'field 4';
fs(5).length = 1;fs(5).type = 'char';fs(5).name = '';
```

Find the records that match at the beginning of the line.

```
grepfields('testfile1','character')
character data 1 1 2 3 1e6 10D6
character data 2 11 22 33 2e6 20D6
character data 3111222333 3e6 30D6
```

```
grepfields('testfile1','character data 2')
character data 2 11 22 33 2e6 20D6
```

Find the records that match, starting the search in column 11.

```
grepfields('testfile1','data 2','none',11)
character data 2 11 22 33 2e6 20D6
```

Search record number 1.

```
grepfields('testfile1','character data 2','none',1,fs)
character data 2 11 22 33 2e6 20D6
```

Limitations

Searches are limited to fields containing character data.

Tips

See `readfields` for a complete discussion of the format and contents of the `fields` argument.

See Also

fopen | readfields

Introduced before R2006a

gridm

Toggle and control display of graticule lines

Syntax

```
gridm
gridm('on')
gridm('off')
gridm('reset')
gridm(linespec)
gridm(MapAxesPropertyName, PropertyValue, ...)
h = gridm(...)
```

Description

`gridm` toggles the display of a latitude-longitude graticule. The choice of meridians and parallels, as well as their graphics properties, depends on the property settings of the map axes.

`gridm('on')` creates the graticule, if it does not yet exist, and makes it visible.

`gridm('off')` makes the graticule invisible.

`gridm('reset')` redraws the graticule using the current map axes properties.

`gridm(linespec)` uses any valid `linespec` to control the graphics properties of the lines in the graticule.

`gridm(MapAxesPropertyName, PropertyValue, ...)` sets the appropriate graticule properties to the desired values. For a description of these property names and values, see “Properties That Control the Grid” on page 1-0 section of the `axesm` property reference page.

`h = gridm(...)` returns the handles of the graticule lines. If both parallels and meridians exist, then `h` is a two-element vector: `h(1)` is the handle to the line comprising the parallels, and `h(2)` is the handle to the line comprising the meridians.

Tips

- You can also create or alter map grid properties using the `axesm` or `setm` functions.
- By default the Clipping property is set to 'off'. Override this setting with the following code:

```
hgrat = gridm('on');  
set(hgrat,'Clipping','on')
```

See Also

`axesm` | `setm`

Introduced before R2006a

grid2image

Display regular data grid as image

Syntax

```
grid2image(Z,R)
grid2image(Z,R,PropertyName,PropertyValue,...)
h = grid2image(...)
```

Description

`grid2image(Z,R)` displays a regular data grid `Z` as an image. The image is displayed in unprojected form, with longitude as `x` and latitude as `y`, producing considerable distortion away from the Equator. `Z` can be *M*-by-*N* or *M*-by-*N*-by-3, and can contain `double`, `uint8`, or `uint16` data. The grid is georeferenced to latitude-longitude by `R`, which can be a geographic raster reference object, a referencing vector, or a referencing matrix.

If `R` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z)` and its `RasterInterpretation` must be 'cells'.

If `R` is a referencing vector, it must be a 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If `R` is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to/from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If `R` is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel.


`grid2image(Z,R,PropertyName,PropertyValue,...)` uses the specified image properties to display the map. See the `image` function reference page for a list of properties that can be changed.

`h = grid2image(...)` returns the handle of the image object displayed.

Examples

Display a regular data grid as an image.

```
load topo
R = georasterref('RasterSize', size(topo), ...
    'Latlim', [-90 90], 'Lonlim', [0 360]);
figure; grid2image(topo, R)
```



See Also

[image](#) | [mapshow](#) | [mapview](#) | [meshm](#) | [surfacem](#) | [surfm](#)

Introduced before R2006a

grn2eqa

Convert from Greenwich to equal area coordinates

Syntax

```
[x,y] = grn2eqa(lat,lon)
[x,y] = grn2eqa(lat,lon,origin)
[x,y] = grn2eqa(lat,lon,origin,ellipsoid)
[x,y] = grn2eqa(lat,lon,origin,units)
mat = grn2eqa(lat,lon,origin...)
```

Description

`[x,y] = grn2eqa(lat,lon)` converts the Greenwich coordinates `lat` and `lon` to the equal-area coordinate points `x` and `y`.

`[x,y] = grn2eqa(lat,lon,origin)` specifies the location in the Greenwich system of the x-y origin (0,0). The two-element vector `origin` must be of the form [`latitude`, `longitude`]. The default places the origin at the Greenwich coordinates (0^o,0^o).

`[x,y] = grn2eqa(lat,lon,origin,ellipsoid)` specifies the ellipsoidal model of the figure of the Earth using `ellipsoid`. `ellipsoid` is a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form [`semimajor_axis` `eccentricity`]. The ellipsoid is spherical by default.

`[x,y] = grn2eqa(lat,lon,origin,units)` specifies the units for the inputs, where `units` is any valid angle units value. The default value is 'degrees'.

`mat = grn2eqa(lat,lon,origin...)` packs the outputs into a single variable.

The `grn2eqa` function converts data from Greenwich-based latitude-longitude coordinates to equal-area x-y coordinates. The opposite conversion can be performed with `eqa2grn`.

Examples

```
lats = [56 34]; longs = [-140 23];  
[x,y] = grn2eqa(lats,longs)
```

```
x =  
  -2.4435    0.4014  
y =  
   0.8290    0.5592
```

See Also

eqa2grn | hista

Introduced before R2006a

gshhs

Read Global Self-Consistent Hierarchical High-Resolution Geography

Syntax

```
S = gshhs(filename)
S = gshhs(filename, latlim, lonlim)
indexfilename = gshhs(filename, 'createindex')
```

Description

`S = gshhs(filename)` reads GSHHG (formerly GSHHS) vector data for the entire world from `filename`. GSHHG files must have names of the form `gshhs_x.b`, `wdb_borders_x.b`, or `wdb_rivers_x.b`, where `x` is one of the letters `c`, `l`, `i`, `h` or `f`, corresponding to increasing resolution (and file size). The result returned in `S` is a polygon or line geographic data structure array (a *geostruct*, with 'Lat' and 'Lon' coordinate fields).

`S = gshhs(filename, latlim, lonlim)` reads a subset of the vector data from `filename`. The limits of the desired data are specified as two-element vectors of latitude, `latlim`, and longitude, `lonlim`, in degrees. The elements of `latlim` and `lonlim` must be in ascending order. Longitude limits range from `[-180 195]`. If `latlim` is empty, the latitude limits are `[-90 90]`. If `lonlim` is empty, the longitude limits are `[-180 195]`.

`indexfilename = gshhs(filename, 'createindex')` creates an index file for faster data access when requesting a subset of a larger dataset. The index file has the same name as the GSHHG data file, but with the extension 'i', instead of 'b' and is written in the same folder as `filename`. The name of the index file is returned, but no coastline data are read. A call using this option should be followed by an additional call to `gshhs` to import actual data. On that and subsequent calls, `gshhs` detects the presence of the index file and uses it to access records by location much faster than it would without an index.

Output Structure

The output structure S contains the following fields. All latitude and longitude values are in degrees.

| Field Name | Field Contents |
|--------------------|---|
| 'Geometry' | 'Line' or 'Polygon' |
| 'BoundingBox' | [minLon minLat; maxLon maxLat] |
| 'Lon' | Coordinate vector |
| 'Lat' | Coordinate vector |
| 'South' | Southern latitude boundary |
| 'North' | Northern latitude boundary |
| 'West' | Western longitude boundary |
| 'East' | Eastern longitude boundary |
| 'Area' | Area of polygon in square kilometers |
| 'Level' | Scalar value ranging from 1 to 4, indicates level in topological hierarchy |
| 'LevelString' | 'land', 'lake', 'island_in_lake', 'pond_in_island_in_lake', or '' |
| 'NumPoints' | Number of points in the polygon |
| 'FormatVersion' | Format version of data file. Positive integer for versions 3 and later; empty for versions 1 and 2. |
| 'Source' | Source of data: 'WDBII' or 'WVS' |
| 'CrossesGreenwich' | Scalar flag: true if the polygon crosses the prime meridian; false otherwise |
| 'GSHHS_ID' | Unique polygon scalar id number, starting at 0 |

For releases 2.0 and higher (FormatVersion 7 and higher), the following additional fields are included in the output structure:

| Field Name | Field Contents |
|-------------|--|
| 'RiverLake' | Scalar flag: <code>true</code> if the polygon is the fat part of a major river and the <code>Level</code> value is set to 2; <code>false</code> otherwise. |
| 'AreaFull' | Area of original full-resolution polygon in units $\frac{1}{10} km^2$. |
| 'Container' | ID of container polygon that encloses this polygon. Set to -1 to indicate none. |
| 'Ancestor' | ID of ancestor polygon in the full resolution set that was the source of this polygon. Set to -1 to indicate none. |

For Release 2.2 and higher (FormatVersion 9 and higher) the following additional field is included in the output structure:

| Field Name | Field Contents |
|-------------------|---|
| 'CrossesDateline' | Scalar flag: <code>true</code> if the polygon crosses the dateline; <code>false</code> otherwise. |

Background

The Global Self-Consistent Hierarchical High-Resolution Geography (formerly the Global Self-Consistent Hierarchical High-Resolution Shoreline) was created by Paul Wessel of the University of Hawaii and Walter H.F. Smith of the NOAA Geosciences Lab. At the full resolution, the data requires 85 MB uncompressed, but lower resolution versions are also provided. This database includes coastlines, major rivers, and lakes. The GSHHG data in various resolutions is available over the Internet from the National Oceanic and Atmospheric Administration, National Geophysical Data Center website.

Version 3 (Release 1.3) of the `gshhs_c.b` (coarse) data set ships with the toolbox in the `toolbox/map/mapdata` folder. For details, type

```
type gshhs_c.txt
```

at the MATLAB command prompt. The `gshhs` function has been qualified on GSHHG releases 1.1 through 2.3.6 (version 15). It should also be able to read newer versions, if they adhere to the same header format as releases 2.0 and 2.1.

Examples


Read Entire Coarse Data Set and Display Levels

Read the entire coarse data set. The example uses a coarse data set because the toolbox includes a sample coarse data set in the `toolbox/map/mapdata` folder. You can use similar code to read intermediate, full-resolution, or high resolution GSHHG data sets.

```
filename = gunzip('gshhs_c.b.gz', tempdir);  
shorelines = gshhs(filename{1});  
delete(filename{1})
```


Display data as a coastline.

```
figure  
worldmap world  
geoshow([shorelines.Lat], [shorelines.Lon])
```



Display each level in a different color.

```
levels = [shorelines.Level];  
land = (levels == 1);  
lake = (levels == 2);  
island = (levels == 3);  
figure  
worldmap world  
geoshow(shorelines(land), 'FaceColor', [0 1 0])  
geoshow(shorelines(lake), 'FaceColor', [0 0 1])  
geoshow(shorelines(island), 'FaceColor', [1 1 0])
```




Read GSHHG Dataset Using an Index

Read the entire coarse data set, creating an index. The example uses a coarse data set because the toolbox includes a sample coarse data set in the `toolbox/map/mapdata` folder. You can use similar code to read intermediate, full-resolution, or high resolution GSHHG data sets.

```
filename = gunzip('gshhs_c.b.gz', tempdir);  
indexname = gshhs(filename{1}, 'createindex');
```

Display Africa as a green polygon. Note that `gshhs` detects and uses the index file automatically.


```
figure
worldmap Africa
```



```
projection = gcm;
latlim = projection.maplatlimit;
lonlim = projection.maplonlimit;
africa = gshhs(filename{1}, latlim, lonlim);
delete(filename{1})
delete(indexname)
```

Sort by descending level to keep smaller level 2 and level 3 features on top.

```
[~,ix] = sort([africa.Level],'descend');  
africa = africa(ix);  
geoshow(africa, 'FaceColor', 'green')  
setm(gca, 'FFaceColor', 'cyan')
```



Tips

- If you are extracting data within specified geographic limits and using data other than coarse resolution, consider creating an index file first. Also, to speed rendering when mapping very large amounts of data, you might want to plot the data as NaN-clipped lines rather than as patches.

- When you specify latitude-longitude limits, polygons that completely fall outside those limits are excluded, but no trimming of features that partially traverse the region is performed. If you want to eliminate data outside of a rectangular region of interest, you can use `maptrim` with the `Lat` and `Lon` fields of the `geostruct` returned by `gshhs` to clip the data to your region and still maintain polygon topology.
- You can read the WDB rivers and borders datasets but the `LevelString` field will be empty. The `Level` values vary from feature to feature but the interpretations of these values are not documented as part of the GSHHG distribution and are therefore not converted to character vectors.

See Also

`dcwdata` | `geoshow` | `maptrim` | `shaperead` | `vmap0data` | `worldmap`

Introduced before R2006a

gtextm

Place text on map using mouse

Syntax

```
h = gtextm(text)
h = gtextm(text,PropertyName,PropertyValue,...)
```

Description

`h = gtextm(text)` places `text`, a string scalar or character vector, at the position selected by mouse input. When you call this function, `gtextm` brings up the current map axes and activates the cursor for mouse-click position entry. `gtextm` returns a text object.

`h = gtextm(text,PropertyName,PropertyValue,...)` allows the specification of any properties supported by the MATLAB text function.

Examples

Create map axes:

```
axesm('sinusoid','FEdgeColor','red')
gtextm('hello world','FontWeight','bold')
```

Click inside the frame and the text appears.

See Also

[axesm](#) | [textm](#)

Introduced before R2006a

gtopo30

Read 30-arc-second global digital elevation data (GTOPO30)

Syntax

```
[Z,refvec] = gtopo30(tilename)
[Z,refvec] = gtopo30(tilename,samplefactor)
[Z,refvec] = gtopo30(tilename,samplefactor,latlim,lonlim)
[Z,refvec] = gtopo30(foldername, ...)
```

Description

`[Z,refvec] = gtopo30(tilename)` reads the GTOPO30 tile specified by `tilename` and returns the result as a regular data grid. `tilename` is a string scalar or character vector which does not include an extension and indicates a GTOPO30 tile in the current folder or on the MATLAB path. If `tilename` is empty or omitted, a file browser will open for interactive selection of the GTOPO30 header file. The data is returned at full resolution with the latitude and longitude limits determined from the GTOPO30 tile. The data grid, `Z`, is returned as an array of elevations. Elevations are given in meters above mean sea level using WGS84 as a horizontal datum. `refvec` is the associated referencing vector.

`[Z,refvec] = gtopo30(tilename,samplefactor)` reads a subset of the elevation data from `tilename`. `samplefactor` is a scalar integer, which when equal to 1 reads the data at its full resolution. When `samplefactor` is an integer `n` greater than one, every `n`th point is read. If `samplefactor` is omitted or empty, it defaults to 1.

`[Z,refvec] = gtopo30(tilename,samplefactor,latlim,lonlim)` reads a subset of the elevation data from `tilename` using the latitude and longitude limits `latlim` and `lonlim` specified in degrees. `latlim` is a two-element vector of the form:

```
[southern_limit northern_limit]
```

Likewise, `lonlim` has the form:

```
[western_limit eastern_limit]
```

If `latlim` and `lonlim` are omitted, the coordinate limits are determined from the file. The latitude and longitude limits are snapped outward to define the smallest possible rectangular grid of GTOPO30 cells that fully encloses the area defined by the input limits. Any cells in this grid that fall outside the extent of the tile are filled with NaN.

`[Z,refvec] = gtopo30(foldername, ...)` is similar to the syntaxes above except that GTOPO30 data are read and concatenated from multiple tiles within a GTOPO30 CD-ROM or folder structure. The `foldername` input is a string scalar or character vector with the name of the folder which contains the GTOPO30 tile folders or GTOPO30 tiles. Within the tile folders are the uncompressed data files. The `foldername` for CD-ROMs distributed by the USGS is the device name of the CD-ROM drive. As with the case with a single tile, any cells in the grid specified by `latlim` and `lonlim` are NaN filled if they are not covered by a tile within `foldername`. `samplefactor` if omitted or empty defaults to 1. `latlim` if omitted or empty defaults to `[-90 90]`. `lonlim` if omitted or empty defaults to `[-180 180]`.

For details on locating GTOPO30 data for download over the Internet, see “Find Geospatial Data Online”.

Examples

Display Data Grid and Overlay Stateline Boundary

To run this example, you must download the GTOPO30 data set. For details on locating this data set for download over the Internet, see “Find Geospatial Data Online”.

Extract and display full resolution data for the state of Massachusetts. Read the stateline polygon boundary and calculate boundary limits.

```
Massachusetts = shaperead('usastatehi','UseGeoCoords',true, ...
    'Selector',{@(name) strcmpi(name,'Massachusetts'),'Name'});
latlim = [min(Massachusetts.Lat(:)) max(Massachusetts.Lat(:))];
lonlim = [min(Massachusetts.Lon(:)) max(Massachusetts.Lon(:))];
```


Read the GTOPO30 data at full resolution.

```
[Z,refvec] = gtopo30('W100N90',1,latlim,lonlim);
```

Display the data grid and overlay the stateline boundary.

```
figure
ax = usamap(Z,refvec);
```

```
ax.SortMethod = 'ChildOrder';  
geoshow(Z,refvec,'DisplayType','surface')  
demcmap(Z)  
geoshow(Massachusetts,'DisplayType','polygon',...  
        'facecolor','none','edgecolor','y')
```



Extract Every 20th Point from Data Set

To run this example, you must download the GTOPO30 data set. For details on locating this data set for download over the Internet, see “Find Geospatial Data Online”.

Extract every 20th point from a tile. Provide an empty filename and select the file interactively.

```
[Z,refvec] = gtopo30([],20);
```

Extract Data That Straddles Two Tiles


To run this example, you must download the GTOPO30 data set. For details on locating this data set for download over the Internet, see “Find Geospatial Data Online”.

Extract data for Thailand, an area which straddles two tiles.

```
latlim = [5.22 20.90];  
lonlim = [96.72 106.38];  
gtopo30s(latlim,lonlim)
```

Extract every fifth data point for Thailand. The code assumes the data is on CD number 3 distributed by the USGS. The CD-device is 'F:\'

```
[Z,refvec] = gtopo30('F:\',5,latlim,lonlim);
worldmap(Z,refvec);
geoshow(Z,refvec,'DisplayType','surface')
demcmap(Z)
```



Extract Every 10th Point from Column of Data

To run this example, you must download the GTOPO30 data set. For details on locating this data set for download over the Internet, see “Find Geospatial Data Online”.

Extract every 10th point from a column of data 5 degrees around the prime meridian. This example assumes the current folder contains GTOPO30 data.

```
[Z,refvec] = gtopo30(pwd,10,[],[-5 5]);
```

See Also

[dted](#) | [globedem](#) | [gtopo30s](#) | [satbath](#) | [tbase](#) | [usgsdem](#)

Introduced before R2006a

gtopo30s

GTOPO30 data filenames for latitude-longitude quadrangle

Syntax

```
tileNames = gtopo30s(latlim,lonlim)
tileNames = gtopo30s(lat,lon)
```

Description

`tileNames = gtopo30s(latlim,lonlim)` returns a cell array of the tile names covering the geographic region for GTOPO30 digital elevation maps (also referred to as “30-arc second” DEMs). `latlim` and `lonlim` specify the region as two-element vectors of latitude and longitude limits in units of degrees.

`tileNames = gtopo30s(lat,lon)` returns a cell array of the tile names covering the geographic region for GTOPO30 digital elevation maps. `lat` and `lon` specify the region as scalar latitude and longitude points.

See Also

`gtopo30`

Introduced before R2006a

handlem

Handles of displayed map objects

Syntax

```
handlem
handlem('taglist')
handlem('prompt')
h = handlem(object)
h = handlem(tagstr)
h = handlem( ____, axes)
h = handlem( ____, axes, 'searchmethod')
h = handlem(handles)
```

Description

handlem displays a dialog box for selecting objects that have their Tag property set.

handlem('taglist') displays a dialog box for selecting objects that have their Tag property set.

handlem('prompt') displays a dialog box for selecting objects based on the objects listed below.

h = handlem(object) returns the graphics objects in the current axes specified by the input, object. The options for the object are defined by the following list:

| | |
|---------------|-------------------------------------|
| 'all' | All children |
| 'clabel' | Contour labels |
| 'contour' | hggroups containing contours |
| 'fillcontour' | hggroups containing filled contours |
| 'frame' | Map frame |
| 'grid' | Map grid lines |

| | |
|--------------|--|
| 'hggroup' | All hggroup objects |
| 'hidden' | Hidden objects |
| 'image' | Untagged image objects |
| 'light' | Untagged light objects |
| 'line' | Untagged line objects |
| 'map' | All objects on the map, excluding the frame and grid |
| 'meridian' | Longitude grid lines |
| 'mlabel' | Longitude labels |
| 'parallel' | Latitude grid lines |
| 'plabel' | Latitude labels |
| 'patch' | Untagged patch objects |
| 'scaleruler' | Scaleruler objects |
| 'surface' | Untagged surface objects |
| 'text' | Untagged text objects |
| 'tissot' | Tissot indicatrices |
| 'visible' | Visible objects |

`h = handlem(tagstr)` returns any graphics objects whose tags match the value of `tagstr`.

`h = handlem(____, axesh)` searches within the specified axes.

`h = handlem(____, axesh, 'searchmethod')` controls the method used to match the object input. If omitted, 'exact' is assumed. Search method 'strmatch' searches for matches that start at the beginning of the tag. Search method 'findstr' searches anywhere within the tag for the object .

`h = handlem(handles)` returns those graphics objects in the input vector of graphics objects that are still valid.

You can apply the prefix 'all' when defining an object type (text, line, patch, light, surface, or image) to find all objects that meet the type criteria (for example, 'allimage'). Without the 'all' prefix, `handlem` returns only objects with an empty tag.

See Also

findobj

Introduced before R2006a

hidem

Hide specified graphic objects on map axes

Syntax

```
hidem  
hidem(handle)  
hidem(object)
```

Description

hidem brings up a dialog box for selecting the objects to hide (set their `Visible` property to 'off').

hidem(handle) hides the objects specified by a vector of handles.

hidem(object) hides those objects specified by the `object`, which can be any string scalar or character vector recognized by the `handlem` function.

See Also

clma | clmo | handlem | namem | showm | tagm

Introduced before R2006a

hista

Bin counts for geographic points using equal-area bins

Syntax

```
[latbin,lonbin,count] = hista(lat,lon)
[latbin,lonbin,count] = hista(lat,lon,binarea)
[latbin,lonbin,count] = hista(lat,lon,binarea,spheroid)
[latbin,lonbin,count]] = hista( ____,angleunits)
```

Description

`[latbin,lonbin,count] = hista(lat,lon)` bins the geographic locations indicated by vectors `lat` and `lon`, using equal area binning on a sphere. The default bin area is 100 square kilometers. The `latbin` and `lonbin` outputs are column vectors indicating the centers of non-empty bins. `count` matches `latbin` and `lonbin` in size, with each element containing a positive integer equal to the number of occurrences in the corresponding bin.

Binning is performed on a mesh within a quadrangle whose latitude and longitude limits match the extrema of the input locations. The input and output latitudes and longitudes are in units of degrees.

`[latbin,lonbin,count] = hista(lat,lon,binarea)` uses the bin size specified by the input `binarea`, which must be in square kilometers

`[latbin,lonbin,count] = hista(lat,lon,binarea,spheroid)` bins the data on the reference spheroid defined by `spheroid`. `spheroid` is a `referenceEllipsoid` (`oblateSpheroid`) object, a `referenceSphere` object, or a vector of the form `[semimajor_axis eccentricity]`. The eccentricity/flattening of the spheroid is used in determining the latitude extent of the bins. The semimajor axis of the spheroid is used to determine the longitude extent of the bins, but if the length unit of the spheroid is unspecified, the mean radius of the earth in kilometers is used as the equatorial radius.

`[latbin,lonbin,count]] = hista(____,angleunits)` where `angleunits` defines the angle units of the inputs and outputs, specified as 'degrees' or 'radians'.

Examples

Bin Latitudes and Longitudes

Create some random latitudes.

```
rng(0, 'twister')  
lats = rand(4)
```

```
lats = 4×4
```

```
    0.8147    0.6324    0.9575    0.9572  
    0.9058    0.0975    0.9649    0.4854  
    0.1270    0.2785    0.1576    0.8003  
    0.9134    0.5469    0.9706    0.1419
```

Create some random longitudes.

```
lons = rand(4)
```

```
lons = 4×4
```

```
    0.4218    0.6557    0.6787    0.6555  
    0.9157    0.0357    0.7577    0.1712  
    0.7922    0.8491    0.7431    0.7060  
    0.9595    0.9340    0.3922    0.0318
```

Bin the data in 50-by-50 km cells (2500 sq km).

```
[lat,lon,num] = hista(lats,lons,2500);
```

```
[lat,lon,num]
```

```
ans = 9×3
```

```
    0.0932   -0.0208    2.0000  
    0.5341    0.3235    1.0000  
    0.9750    0.3235    2.0000  
    0.0932    0.6678    2.0000  
    0.5341    0.6678    1.0000  
    0.9750    0.6678    4.0000  
    0.0932    1.0122    1.0000
```

| | | |
|--------|--------|--------|
| 0.5341 | 1.0122 | 1.0000 |
| 0.9750 | 1.0122 | 2.0000 |

See Also

`eqa2grn` | `grn2eqa` | `histr`

Introduced before R2006a

histr

Histogram for geographic points with equirectangular bins

Syntax

```
[lat,lon,num,wnum] = histr(lats,lons)
[lat,lon,num,wnum] = histr(lats,lons,units)
[lat,lon,num,wnum] = histr(lats,lons,bindensty)
```

Description

`[lat,lon,num,wnum] = histr(lats,lons)` returns the center coordinates of equal-rectangular bins and the number of observations, `num`, falling in each based on the geographically distributed input data. Additionally, an area-weighted observation value, `wnum`, is returned. `wnum` is the bin's `num` divided by its normalized area. The largest bin has the same `num` and `wnum`; a smaller bin has a larger `wnum` than `num`.

`[lat,lon,num,wnum] = histr(lats,lons,units)` where `units` specifies the angle unit. The default value is 'degrees'.

`[lat,lon,num,wnum] = histr(lats,lons,bindensty)` sets the number of bins per angular unit. For example, if `units` is 'degrees', a `bindensty` of 10 would be 10 bins per degree of latitude or longitude, resulting in 100 bins per *square* degree. The default is one cell per angular unit.

The `histr` function sorts geographic data into equirectangular bins for histogram purposes. Equirectangular in this context means that each bin has the same angular measurement on each side (e.g., 1° -by- 1°). Consequently, the result is not an equal-area histogram. The `hista` function provides that capability. However, the results of `histr` can be weighted by their area bias to correct for this, in some sense.

Examples

Bin Latitudes and Longitudes with Equirectangular Bins

Create some random latitudes.

```
rng(0, 'twister')
lats = rand(4)

lats = 4×4

    0.8147    0.6324    0.9575    0.9572
    0.9058    0.0975    0.9649    0.4854
    0.1270    0.2785    0.1576    0.8003
    0.9134    0.5469    0.9706    0.1419
```

Create some random longitudes.

```
lons = rand(4)

lons = 4×4

    0.4218    0.6557    0.6787    0.6555
    0.9157    0.0357    0.7577    0.1712
    0.7922    0.8491    0.7431    0.7060
    0.9595    0.9340    0.3922    0.0318
```

Bin the data in 0.5-by-0.5 degree cells (two bins per degree). The bins centered at 0.75°N are slightly smaller in area than the others. `wnum` reflects the relative count per normalized unit area.

```
[lat,lon,num,wnum] = histr(lats,lons,2);

[lat,lon,num,wnum]

ans = 4×4

    0.2500    0.2500    3.0000    3.0000
    0.7500    0.2500    2.0000    2.0002
    0.2500    0.7500    3.0000    3.0000
    0.7500    0.7500    8.0000    8.0006
```


See Also

filterm|hista

Introduced before R2006a

imbedm

Encode data points into regular data grid

Syntax

```
Z = imbedm(lat, lon, value, Z, R)
Z = imbedm(lat, lon, value, Z, R, units)
[Z, indxPointOutsideGrid] = imbedm(...)
```

Description

`Z = imbedm(lat, lon, value, Z, R)` resets certain entries of a regular data grid, `Z`. `R` can be a geographic raster reference object, a referencing vector, or a referencing matrix.

If `R` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z)`.

If `R` is a referencing vector, it must be a 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If `R` is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to or from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If `R` is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. Nearest-neighbor interpolation is used by default. NaN is returned for points outside the grid limits or for which `lat` or `lon` contain NaN. All angles are in units of degrees.

`Z = imbedm(lat, lon, value, Z, R, units)` specifies the units of the vectors `lat` and `lon`, where `units` is any valid angle units character vector ('degrees' by default).

`[Z, indxPointOutsideGrid] = imbedm(...)` returns the indices of `lat` and `lon` corresponding to points outside the grid in the variable `indxPointOutsideGrid`.

Examples

Create a simple grid map and embed new values in it:

```
Z = ones(3,6)
```

```
Z =
```

```
    1    1    1    1    1    1
    1    1    1    1    1    1
    1    1    1    1    1    1
```

```
refvec = [1/60 90 -180]
```

```
refvec =
```

```
    0.0167    90.0000 -180.0000
```

```
newgrid = imbedm([23 -23], [45 -45],[5 5],Z,refvec)
```

```
newgrid =
```

```
    1    1    1    1    1    1
    1    1    5    5    1    1
    1    1    1    1    1    1
```

See Also

`latlon2val` | `setpostn`

Introduced before R2006a

ind2rgb8

Convert indexed image to uint8 RGB image

Syntax

```
RGB = ind2rgb8(X,cmap)
```

Description

`RGB = ind2rgb8(X,cmap)` creates an RGB image of class `uint8`. `X` must be `uint8`, `uint16`, or `double`, and `cmap` must be a valid MATLAB colormap.

Examples

```
% Convert the 'concord_ortho_e.tif' image to RGB.  
[X, cmap] = imread('concord_ortho_e.tif');  
RGB = ind2rgb8(X, cmap);  
R = worldfileread('concord_ortho_e.tfw');  
mapshow(RGB, R);
```

See Also

`ind2rgb`

Introduced before R2006a

ingeoquad

True for points inside or on lat-lon quadrangle

Syntax

```
tf = ingeoquad(lat, lon, latlim, lonlim)
```

Description

`tf = ingeoquad(lat, lon, latlim, lonlim)` returns an array `tf` that has the same size as `lat` and `lon`. `tf(k)` is true if and only if the point `lat(k)`, `lon(k)` falls within or on the edge of the geographic quadrangle defined by `latlim` and `lonlim`. `latlim` is a vector of the form `[southern-limit northern-limit]`, and `lonlim` is a vector of the form `[western-limit eastern-limit]`. All angles are in units of degrees.

Examples

- 1 Load and display a digital elevation model (DEM) including the Korean Peninsula:

```
korea = load('korea');
R = refvecToGeoRasterReference(korea.refvec, size(korea.map));
figure('Color','white')
worldmap([20 50],[90 150])
geoshow(korea.map, R, 'DisplayType', 'texturemap');
demcmap(korea.map)
```

- 2 Outline the quadrangle containing the DEM:


```
[outlineLat, outlineLon] = outlinegeoquad(R.Latlim, ...
    R.Lonlim, 90, 5);
geoshow(outlineLat,outlineLon,'DisplayType','line', ...
    'Color','black')
```

- 3 Generate a track that crosses the DEM:

```
[lat, lon] = track2(23, 110, 48, 149, [1 0], 'degrees', 20);  
geoshow(lat, lon, 'DisplayType', 'line')
```

- 4** Identify and mark points on the track that fall within the quadrangle outlining the DEM:

```
tf = ingeoquad(lat, lon, R.Latlim, R.Lonlim);  
geoshow(lat(tf), lon(tf), 'DisplayType', 'point')
```



See Also

[inpolygon](#) | [intersectgeoquad](#)

Introduced in R2008a

intersectgeoquad

Intersection of two latitude-longitude quadrangles

Syntax

```
[latlim, lonlim] = intersectgeoquad(latlim1, lonlim1, latlim2,  
lonlim2)
```

Description

[latlim, lonlim] = intersectgeoquad(latlim1, lonlim1, latlim2, lonlim2) computes the intersection of the quadrangle defined by the latitude and longitude limits latlim1 and lonlim1, with the quadrangle defined by the latitude and longitude limits latlim2 and lonlim2. latlim1 and latlim2 are two-element vectors of the form [southern-limit northern-limit]. Likewise, lonlim1 and lonlim2 are two-element vectors of the form [western-limit eastern-limit]. All input and output angles are in units of degrees. The intersection results are given in the output arrays latlim and lonlim. Given an arbitrary pair of input quadrangles, there are three possible results:

- 1** *The quadrangles fail to intersect.* In this case, both latlim and lonlim are empty arrays.
- 2** *The intersection consists of a single quadrangle.* In this case, latlim (like latlim1 and latlim2) is a two-element vector that has the form [southern-limit northern-limit], where southern-limit and northern-limit represent scalar values. lonlim (like lonlim1 and lonlim2), is a two-element vector that has the form [western-limit eastern-limit], with a pair of scalar limits.
- 3** *The intersection consists of a pair of quadrangles.* This can happen when longitudes wrap around such that the eastern end of one quadrangle overlaps the western end of the other and vice versa. For example, if lonlim1 = [-90 90] and lonlim2 = [45 -45], there are two intervals of overlap: [-90 -45] and [45 90]. These limits are returned in lonlim in separate rows, forming a 2-by-2 array. In our example (assuming that the latitude limits overlap), lonlim would equal [-90 -45; 45 90]. It still has the form [western-limit eastern-limit], but western-limit

and `eastern-limit` are 2-by-1 rather than scalar. The two output quadrangles have the same latitude limits, but these are replicated so that `latlim` is also 2-by-2.

To continue the example, if `latlim1 = [0 30]` and `latlim2 = [20 50]`, `latlim` equals `[20 30; 20 30]`. The form is still `[southern-limit northern-limit]`, but in this case `southern-limit` and `northern-limit` are 2-by-1.

Examples

Example 1

Nonintersecting quadrangles:

```
[latlim, lonlim] = intersectgeoquad( ...
    [-40 -60], [-180 180], [40 60], [-180 180])
latlim =
    []
lonlim =
    []
```

Example 2

Intersection is a single quadrangle:

```
[latlim, lonlim] = intersectgeoquad( ...
    [-40 60], [-120 45], [-60 40], [160 -75])
latlim =
    -40    40
lonlim =
    -120   -75
```

Example 3

Intersection is a pair of quadrangles:

```
[latlim, lonlim] = intersectgeoquad( ...
    [-30 90],[-10 -170],[-90 30],[170 10])
```



```

latlim =
  -30   30
  -30   30

lonlim =
  -10   10
  170 -170

```

Example 4

Inputs and output fully encircle the planet:

```

[latlim, lonlim] = intersectgeoquad( ...
    [-30 90],[-180 180],[-90 30],[0 360])

```

```

latlim =
  -30   30

```

```

lonlim =
  -180  180

```

Example 5

Find and map the intersection of the bounding boxes of adjoining U.S. states:

```

usamap({'Minnesota','Wisconsin'})
S = shaperead('usastatehi','UseGeoCoords',true,'Selector',...
    {@(name) any(strcmp(name,{'Minnesota','Wisconsin'})), 'Name'});
geoshow(S, 'FaceColor', 'y')
textm([S.LabelLat], [S.LabelLon], {S.Name},...
    'HorizontalAlignment', 'center')
latlimMN = S(1).BoundingBox(:,2)

latlimMN =
    43.4995    49.3844


lonlimMN = S(1).BoundingBox(:,1)

lonlimMN =
   -97.2385   -89.5612

latlimWI = S(2).BoundingBox(:,2)

```

```
latlimWI =  
    42.4918    47.0773  
  
lonlimWI = S(2).BoundingBox(:,1)'  
  
lonlimWI =  
   -92.8892   -86.8059  
  
[latlim lonlim] = ...  
    intersectgeoquad(latlimMN, lonlimMN, latlimWI, lonlimWI)  
  
latlim =  
    43.4995    47.0773  
  
lonlim =  
   -92.8892   -89.5612  
  
geoshow(latlim([1 2 2 1 1]), lonlim([1 1 2 2 1]), ...  
    'DisplayType','polygon','FaceColor','m')
```



Tips

`latlim1` and `latlim2` should normally be given in order of increasing numerical value. No error will result if, for example, `latlim1(2) < latlim1(1)`, but the outputs will both be empty arrays.

No such restriction applies to `lonlim1` and `lonlim2`. The first element is always interpreted as the western limit, even if it exceeds the second element (the eastern limit). Furthermore, `intersectgeoquad` correctly handles whatever longitude-wrapping convention may have been applied to `lonlim1` and `lonlim2`.

In terms of output, `intersectgeoquad` wraps `lonlim` such that all elements fall in the closed interval `[-180 180]`. This means that if (one of) the output quadrangle(s) crosses the 180° meridian, its western limit exceeds its eastern limit. The result would be such that

```
lonlim(2) < lonlim(1)
```

if the intersection comprises a single quadrangle or

```
lonlim(k,2) < lonlim(k,1)
```

where k equals 1 or 2 if the intersection comprises a pair of quadrangles.

If `abs(diff(lonlim1))` or `abs(diff(lonlim2))` equals 360, its quadrangle is interpreted as a latitudinal zone that fully encircles the planet, bounded only by one parallel on the south and another parallel on the north. If two such quadrangles intersect, `lonlim` is set to `[-180 180]`.

If you want to display geographic quadrangles generated by this function or any other which are more than one or two degrees in extent, they may not follow curved meridians and parallels very well. The degree of departure depends on the extent of the quadrangle, the map projection, and the map scale. In such cases, you can interpolate intermediate vertices along quadrangle edges with the `outlinegeoquad` function.

See Also

`ingeoquad` | `outlinegeoquad`

Introduced in R2008a

inputm

Latitudes and longitudes of mouse-click locations

Syntax

```
[lat, lon] = inputm
[lat, lon] = inputm(n)
[lat, lon] = inputm(n,h)
[lat, lon, button] = inputm(n)
MAT = inputm(...)
```

Description

`[lat, lon] = inputm` returns the latitudes and longitudes in geographic coordinates of points selected by mouse clicks on a displayed grid. The point selection continues until the return key is pressed.

`[lat, lon] = inputm(n)` returns `n` points specified by mouse clicks.

`[lat, lon] = inputm(n,h)` prompts for points from the map axes specified by the handle `h`. If omitted, the current axes (`gca`) is assumed.

`[lat, lon, button] = inputm(n)` returns a third result, `button`, that contains a vector of integers specifying which mouse button was used (1,2,3 from left) or ASCII numbers if a key on the keyboard was used.

`MAT = inputm(...)` returns a single matrix, where `MAT = [lat lon]`.

Tips

`inputm` works much like the standard MATLAB `ginput`, except that the returned values are latitudes and longitudes extracted from the projection, rather than axes x - y coordinates. If you click outside of the projection bounds (beyond the map frame in the corners of a Robinson projection, for example), no coordinates are returned for that location.

`inputm` cannot be used with a 3-D display, including those created using `globe`.

See Also

`gcpmap` | `ginput`

Introduced before R2006a

interpm

Densify latitude-longitude sampling in lines or polygons

Syntax

```
[latout,lonout] = interpm(lat,lon,maxdiff)
[latout,lonout] = interpm(lat,lon,maxdiff,method)
[latout,lonout] = interpm(lat,lon,maxdiff,method,units)
```

Description

`[latout,lonout] = interpm(lat,lon,maxdiff)` fills in any gaps in latitude (`lat`) or longitude (`lon`) data vectors that are greater than a defined tolerance `maxdiff` apart in either dimension. The angle units of the three inputs need not be specified, but they must be identical. `latout` and `lonout` are the new latitude and longitude data vectors, in which any gaps larger than `maxdiff` in the original vectors have been filled with additional points. The default method of interpolation used by `interpm` is linear.

`[latout,lonout] = interpm(lat,lon,maxdiff,method)` interpolates between vector data coordinate points using a specified interpolation method. Valid interpolation methods are 'gc' for great circle, 'rh' for rhumb line, and 'lin' for linear interpolation.

`[latout,lonout] = interpm(lat,lon,maxdiff,method,units)` specifies the units used, where `units` is any valid angle unit. The default is 'degrees'.

Examples

```
lat = [1 2 4 5]; lon = [7 8 9 11];
[latout,lonout] = interpm(lat,lon,1);
[latout lonout]
```

```
ans =
    1.0000    7.0000
    2.0000    8.0000
```

| | |
|--------|---------|
| 3.0000 | 8.5000 |
| 4.0000 | 9.0000 |
| 4.5000 | 10.0000 |
| 5.0000 | 11.0000 |

See Also

`intrplat` | `intrplon`

Introduced before R2006a

intrinsicToGeographic

Package: map.rasterref

Transform intrinsic to geographic coordinates

Syntax

```
[lat,lon] = intrinsicToGeographic(R,xIntrinsic,yIntrinsic)
```

Description

[lat,lon] = intrinsicToGeographic(R,xIntrinsic,yIntrinsic) returns the geographic coordinates corresponding to intrinsic coordinates (xIntrinsic, yIntrinsic) in geographic raster R.

Input Arguments

R — Geographic raster

GeographicCellsReference or GeographicPostingsReference object

Geographic raster, specified as a GeographicCellsReference or GeographicPostingsReference object.

xIntrinsic — x-coordinates in intrinsic coordinate system

numeric array

x-coordinates in intrinsic coordinate system, specified as a numeric array. xIntrinsic coordinates can be outside the bounds of the raster R.

Data Types: single | double

yIntrinsic — y-coordinates in intrinsic coordinate system

numeric array

y-coordinates in intrinsic coordinate system, specified as a numeric array. `yIntrinsic` is the same size as `xIntrinsic`. `yIntrinsic` coordinates can be outside the bounds of the raster `R`.

Data Types: `single` | `double`

Output Arguments

lat — Latitude coordinates

numeric array

Latitude coordinates, returned as a numeric array. `lat` is the same size as `xIntrinsic`.

When a point (`xIntrinsic(k)`, `yIntrinsic(k)`) is outside the bounds of raster `R`, `lat(k)` and `lon(k)` are extrapolated in the geographic coordinate system. However, for any point that extrapolates to a latitude beyond the poles (latitude outside the range `[-90, 90]` degrees), `lat(k)` and `lon(k)` are set to `NaN`.

Data Types: `double`

lon — Longitude coordinates

numeric array

Longitude coordinates, returned as a numeric array. `lon` is the same size as `xIntrinsic`.

When a point (`xIntrinsic(k)`, `yIntrinsic(k)`) is outside the bounds of raster `R`, `lat(k)` and `lon(k)` are extrapolated in the geographic coordinate system. However, for any point that extrapolates to a latitude beyond the poles (latitude outside the range `[-90, 90]` degrees), `lat(k)` and `lon(k)` are set to `NaN`.

Data Types: `double`

See Also

`geographicToIntrinsic` | `intrinsicToWorld` | `intrinsicXToLongitude` | `intrinsicYToLatitude`

Introduced in R2013b

intrinsicToWorld

Package: map.rasterref

Transform intrinsic to planar world coordinates

Syntax

```
[xWorld,yWorld] = intrinsicToWorld(R,xIntrinsic,yIntrinsic)
```

Description

`[xWorld,yWorld] = intrinsicToWorld(R,xIntrinsic,yIntrinsic)` returns the planar world coordinates corresponding to intrinsic coordinates (`xIntrinsic`, `yIntrinsic`) in map raster `R`. If a point is outside the bounds of `R`, then `intrinsicToWorld` extrapolates the `xWorld` and `yWorld` coordinates.

Input Arguments

R — Map raster

MapCellsReference or MapPostingsReference object

Map raster, specified as a MapCellsReference or MapPostingsReference object.

xIntrinsic — x-coordinates in intrinsic coordinate system

numeric array

x-coordinates in intrinsic coordinate system, specified as a numeric array. `xIntrinsic` coordinates can be outside the bounds of the raster `R`.

Data Types: single | double

yIntrinsic — y-coordinates in intrinsic coordinate system

numeric array

y-coordinates in intrinsic coordinate system, specified as a numeric array. `yIntrinsic` is the same size as `xIntrinsic`. `yIntrinsic` coordinates can be outside the bounds of the raster `R`.

Data Types: `single` | `double`

Output Arguments

`xWorld` — x-coordinates in the world coordinate system

numeric array

x-coordinates in the world coordinate system, specified as a numeric array. `xWorld` is the same size as `xIntrinsic`. When `xIntrinsic(k)` is outside the bounds of `R`, `intrinsicToWorld` extrapolates the `xWorld` coordinate.

Data Types: `double`

`yWorld` — y-coordinates in the world coordinate system

numeric array

y-coordinates in the world coordinate system, specified as a numeric array. `yWorld` is the same size as `xIntrinsic`. When `yIntrinsic(k)` is outside the bounds of `R`, `intrinsicToWorld` extrapolates the `yWorld` coordinate.

Data Types: `double`

See Also

`intrinsicToGeographic` | `intrinsicXToLongitude` | `intrinsicYToLatitude` | `worldToIntrinsic`

Introduced in R2013b

intrinsicXToLongitude

Package: map.rasterref

Convert from intrinsic x to longitude coordinates

Syntax

```
lon = intrinsicXToLongitude(R,xIntrinsic)
```

Description

`lon = intrinsicXToLongitude(R,xIntrinsic)` returns the longitude of the meridian corresponding to the x -coordinate `xIntrinsic` in the intrinsic coordinate system, based on the relationship defined by geographic raster `R`.

Input Arguments

R — Geographic raster

GeographicCellsReference or GeographicPostingsReference object

Geographic raster, specified as a GeographicCellsReference or GeographicPostingsReference object.

xIntrinsic — x -coordinates in intrinsic coordinate system

numeric array

x -coordinates in intrinsic coordinate system, specified as a numeric array. `xIntrinsic` coordinates can be outside the bounds of the raster `R`.

Data Types: single | double

Output Arguments

lon — Longitude coordinates

numeric array

Longitude coordinates, returned as a numeric array. `lon` is the same size as `xIntrinsic`.

When a point has intrinsic x -coordinate outside the bounds of raster `R`, `lon(k)` is extrapolated outside the longitude limits. Elements of `xIntrinsic` with value `NaN` map to `NaN` in `lon`. Longitude values are not wrapped.

Data Types: `double`

See Also

`intrinsicToGeographic` | `intrinsicYToLatitude` | `longitudeToIntrinsicX`

Introduced in R2013b

intrinsicYToLatitude

Package: map.rasterref

Convert from intrinsic *y* to latitude coordinates

Syntax

```
lat = intrinsicYToLatitude(R,yIntrinsic)
```

Description

`lat = intrinsicYToLatitude(R,yIntrinsic)` returns the latitude of the small circle corresponding to the *y*-coordinate `yIntrinsic` in the intrinsic coordinate system, based on the relationship defined by geographic raster *R*.

Input Arguments

R — Geographic raster

GeographicCellsReference or GeographicPostingsReference object

Geographic raster, specified as a GeographicCellsReference or GeographicPostingsReference object.

yIntrinsic — y-coordinates in intrinsic coordinate system

numeric array

y-coordinates in intrinsic coordinate system, specified as a numeric array. `yIntrinsic` coordinates can be outside the bounds of the raster *R*.

Data Types: single | double

Output Arguments

lat — Latitude coordinates

numeric array

Latitude coordinates, returned as a numeric array. `lat` is the same size as `yIntrinsic`.

When a point has intrinsic *y*-coordinate outside the bounds of raster *R*, `lat(k)` is extrapolated outside the latitude limits. However, when a point extrapolates to a latitude beyond the poles (latitude outside the range [-90, 90] degrees), `lat(k)` is set to NaN. Elements of `yIntrinsic` with value NaN map to NaN in `lat`.

Data Types: double

See Also

`intrinsicToGeographic` | `intrinsicXToLongitude` | `latitudeToIntrinsicY`

Introduced in R2013b

intrplat

Interpolate latitude at given longitude

Syntax

```
newlat = intrplat(long,lat,newlong)
newlat = intrplat(long,lat,newlong,method)
newlat = intrplat(long,lat,newlong,method,units)
```

Description

`newlat = intrplat(long,lat,newlong)` returns an interpolated latitude, `newlat`, corresponding to a longitude `newlong`. `long` must be a monotonic vector of longitude values. The actual entries must be monotonic; that is, the longitude vector `[350 357 3 10]` is not allowed even though the geographic *direction* is unchanged (use `[350 357 363 370]` instead). `lat` is a vector of the latitude values paired with each entry in `long`.

`newlat = intrplat(long,lat,newlong,method)` specifies the method of interpolation employed, listed in the table below.

| Method | Description |
|----------|--|
| 'linear' | Linear, or Cartesian, interpolation (default) |
| 'pchip' | Piecewise cubic Hermite interpolation |
| 'rh' | Returns interpolated points that lie on rhumb lines between input data |
| 'gc' | Returns interpolated points that lie on great circles between input data |

`newlat = intrplat(long,lat,newlong,method,units)` specifies the units used, where `units` is any valid angle units string scalar or character vector. The default is 'degrees'.

The function `intrplat` is a geographic data analogy of the standard MATLAB function `interp1`.

Examples

Compare the results of the various methods:

```
lats = [25 45]; longs = [30 60];  
newlat = intrplat(longs,lats,45,'linear')
```

```
newlat =  
    35
```

```
newlat = intrplat(longs,lats,45,'rh')
```

```
newlat =  
    35.6213
```

```
newlat = intrplat(longs,lats,45,'gc')
```

```
newlat =  
    37.1991
```

Tips

There are separate functions for interpolating latitudes and longitudes, for although the cases are identical when using those methods supported by `interp1`, when latitudes and longitudes are treated like the spherical angles they are (using `'rh'` or `'gc'`), the results are different. Compare the example above to the example under `intrplon`, which reverses the values of latitude and longitude.

See Also

`interp1` | `intrplon`

Introduced before R2006a

intrplon

Interpolate longitude at given latitude

Syntax

```
newlon = intrplon(lat,lon,newlat)
newlon = intrplon(lat,lon,newlat,method)
newlon = intrplon(lat,lon,newlat,method,units)
```

Description

`newlon = intrplon(lat,lon,newlat)` returns an interpolated longitude, `newlon`, corresponding to a latitude `newlat`. `lat` must be a monotonic vector of longitude values. `lon` is a vector of the longitude values paired with each entry in `lat`.

`newlon = intrplon(lat,lon,newlat,method)` specifies the method of interpolation employed, listed in the table below.

| Method | Description |
|----------|--|
| 'linear' | Linear, or Cartesian, interpolation (default) |
| 'pchip' | Piecewise cubic Hermite interpolation |
| 'rh' | Returns interpolated points that lie on rhumb lines between input data |
| 'gc' | Returns interpolated points that lie on great circles between input data |

`newlon = intrplon(lat,lon,newlat,method,units)` specifies the units used, where `units` is any valid angle units string scalar or character vector. The default is 'degrees'.

The function `intrplon` is a geographic data analogy of the MATLAB function `interp1`.

Examples

Compare the results of the various methods:

```
long = [25 45]; lat = [30 60];  
newlon = intrplon(lat, long, 45, 'linear')
```

```
newlon =  
    35
```

```
newlon = intrplon(lat, long, 45, 'rh')
```

```
newlon =  
    33.6515
```

```
newlon = intrplon(lat, long, 45, 'gc')
```

```
newlon =  
    32.0526
```

Tips

There are separate functions for interpolating latitudes and longitudes, for although the cases are identical when using those methods supported by `interp1`, when latitudes and longitudes are treated like the spherical angles they are (using 'rh' or 'gc'), the results are different. Compare the previous example to the example under `intrplat`, which reverses the values of latitude and longitude.

See Also

`interp1` | `intrplat`

Introduced before R2006a

inverse

Package: map.geodesy

Convert authalic, conformal, isometric, or rectifying latitude to geodetic latitude

Syntax

```
phi = inverse(converter, lat)
phi = inverse(converter, lat, angleUnit)
```

Description

`phi = inverse(converter, lat)` returns the geodetic latitude coordinates corresponding to authalic, conformal, isometric, or rectifying latitude coordinates `lat`.

`phi = inverse(converter, lat, angleUnit)` specifies the units of output `phi`.

Examples

Convert Conformal Latitude Values to Geodetic Values

```
chi = [-90 -67.3637 -44.8077 -22.3643 0 22.3643 44.8077 67.3637 90];
conv = map.geodesy.ConformalLatitudeConverter(wgs84Ellipsoid);
phi = inverse(conv, chi)
```

```
phi =
```

```
-90.0000 -67.5000 -45.0000 -22.5000 0 22.5000 45.0000 67.5000 90
```

Convert Isometric to Geodetic Latitude, in Radians

```
psi = [-Inf -1.6087 -0.87663 -0.40064 0 0.40064 0.87663 1.6087 Inf];  
conv = map.geodesy.IsometricLatitudeConverter(wgs84Ellipsoid);  
phi = inverse(conv,psi,'radians')
```

```
phi =
```

```
-1.5708 -1.1781 -0.7854 -0.3927 0 0.3927 0.7854 1.1781 1.5708
```

Input Arguments

converter — Latitude converter

`AuthalicLatitudeConverter`, `ConformalLatitudeConverter`, `IsometricLatitudeConverter`, or `RectifyingLatitudeConverter` object

Latitude converter, specified as an `AuthalicLatitudeConverter`, `ConformalLatitudeConverter`, `IsometricLatitudeConverter`, or `RectifyingLatitudeConverter` object.

lat — Latitude coordinates to convert

numeric scalar, vector, matrix, or N-D array

Latitude coordinates to convert, specified as a numeric scalar, vector, matrix, or N-D array.

The interpretation of `lat` depends on the latitude converter. If the conversion is:

- `authalic`, `lat` represents the variable β (beta).
- `conformal`, `lat` represents χ (chi).
- `isometric`, `lat` represents ψ (psi). `lat` is a dimensionless number and does not have an angle unit.
- `rectifying`, `lat` represents μ (mu).

For `authalic`, `conformal`, and `rectifying` conversions, the values of `lat` must be consistent with `angleUnit`.

angleUnit — Unit of latitude coordinates

'degrees' (default) | 'radians'

Units of latitude coordinates, specified as 'degrees' or 'radians'.

Output Arguments

phi — Geodetic latitude coordinates

numeric scalar, vector, matrix, or N-D array

Geodetic latitude coordinates, specified as a numeric scalar value, vector, matrix, or N-D array. `phi` is the same size as `lat`. If `angleUnit` is not supplied, `phi` is in degrees. Otherwise, values of `phi` are consistent with the units of `angleUnit`.

Data Types: `single` | `double`

See Also

`forward`

Introduced in R2013a

map.geodesy.isDegree

True if input matches 'degree' and false if 'radian'

Syntax

```
tf = map.geodesy.isDegree(angleUnit)
```

Description

`tf = map.geodesy.isDegree(angleUnit)` returns true if `angleUnit` is a partial match for 'degree' (or 'degrees') and false if `angleUnit` is a partial match for 'radian' (or 'radians'). If `angleUnit` matches neither 'degrees' or 'radians', `map.geodesy.isDegree` returns an error.

Examples

Test Inputs to a Function for Validity Before Processing

Create a function to calculate a cosine. In the function, use `map.geodesy.isDegree` to check the validity of the inputs.

```
function y = cosine(x, angleUnit)
% X can be in either degrees or radians

if map.geodesy.isDegree(angleUnit)
    y = cosd(x);
else
```



```
    y = cos(x);  
end
```

Input Arguments

angleUnit — Angle unit value

'degree' | 'radian'

Angle unit value, specified as 'degree' or 'radian'.

Data Types: char

Output Arguments

tf — True/false flag indicating if a match was found

logical scalar

True/false flag indicating if a match was found, returned as a logical scalar.

See Also

Introduced in R2013a

isempty

Determine if geographic or planar vector is empty

Syntax

```
tf = isempty(v)
```

Description

`tf = isempty(v)` determines whether the geographic or planar vector `v` is empty.

Examples

Check If a Geopoint Vector Is Empty

Create a default geopoint vector.

```
gp = geopoint()
```

```
gp =
```

```
0x1 geopoint vector with properties:
```

```
Collection properties:
```

```
Geometry: 'point'
```

```
Metadata: [1x1 struct]
```

```
Feature properties:
```

```
Latitude: []
```

```
Longitude: []
```

Check if the geopoint vector is empty. A returned value of 1 (true) indicates the vector is empty.

```
isempty(gp)
```

```
ans = logical
      1
```

Create a second geoint vector, specifying a geographic point. Confirm that this vector is not empty. A returned value of 0 (false) indicates the vector is not empty.

```
gp2 = geoint(42.356, -71.101)

gp2 =
  1x1 geoint vector with properties:

  Collection properties:
    Geometry: 'point'
    Metadata: [1x1 struct]
  Feature properties:
    Latitude: 42.3560
    Longitude: -71.1010
```

```
isempty(gp2)

ans = logical
      0
```

Input Arguments

v — Geographic or planar vector

`geoint`, `geoshape`, `mappoint`, or `mapshape` object

Geographic or planar vector, specified as a `geoint`, `geoshape`, `mappoint`, or `mapshape` object.

Output Arguments

tf — Flag indicating geographic or planar vector is empty

logical scalar

Flag indicating geographic or planar vector is empty, returned as a logical scalar. `tf` is True when `v` is empty.

Data Types: logical

Introduced in R2012a

isfield

Determine if dynamic property exists in geographic or planar vector

Syntax

```
tf = isfield(v,name)
tf = isfield(v,names)
```

Description

`tf = isfield(v,name)` determines whether the value specified by `name` is a dynamic property in geographic or planar vector `v`.

`tf = isfield(v,names)` determines whether each value specified by `names` is a dynamic property in `v`.

Examples

Check If a Dynamic Property Exists in a Mappoint Vector

Create a mappoint vector.

```
mp = mappoint(-33.961, 18.484, 'Name', 'Cape Town')
```

```
mp =
  1x1 mappoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  X: -33.9610
  Y: 18.4840
  Name: 'Cape Town'
```

Check if individual properties are dynamic properties in the mappoint vector.

```
isfield(mp, 'X')  
  
ans = logical  
     0
```

This result is 0 (false) because property X in the mappoint vector is not a dynamic property.

```
isfield(mp, 'Name')  
  
ans = logical  
     1
```

This result is 1 (true) because the property Name is a dynamic property that exists in the mappoint vector.

```
isfield(mp, 'Latitude')  
  
ans = logical  
     0
```

This result is 0 (false) because the dynamic property Latitude does not exist in the mappoint vector.

Check If Multiple Dynamic Properties Exist in a Geoshape Vector

Create a geoshape vector.

```
gs = geoshape(-33.961, 18.484, 'Name', 'Cape Town')  
  
gs =  
1x1 geoshape vector with properties:  
  
Collection properties:  
    Geometry: 'line'  
    Metadata: [1x1 struct]  
Vertex properties:  
    Latitude: -33.9610
```

```
Longitude: 18.4840
Feature properties:
  Name: 'Cape Town'
```

Check if a group of properties are dynamic properties in the geoshape vector.

```
tf = isfield(gs, {'Latitude', 'longitude', 'Name'})
```

```
tf = 1x3 logical array
```

```
    0    0    1
```

The first element of `tf` is 0 (false) because the property `Latitude` exists in the geoshape vector but is not a dynamic property. The second element of `tf` is 0 (false) because the property `longitude` does not exist in the geoshape vector (property names are case-sensitive.) The last element of `tf` is 1 (true), indicating that `Name` is a dynamic property in the geoshape vector.

Input Arguments

v — Geographic or planar vector

geopoint, geoshape, mappoint, or mapshape object

Geographic or planar vector, specified as a `geopoint`, `geoshape`, `mappoint`, or `mapshape` object.

name — Name of single property

character vector

Name of a single property, specified as a character vector.

names — Name of multiple properties

cell array of character vectors

Name of multiple properties, specified as a cell array of character vectors.

Output Arguments

tf — Flag indicating the dynamic property exists in the geographic or planar vector

logical scalar or vector

Flag indicating the dynamic property exists in the geographic or planar vector, returned as a logical scalar or vector. Each element of **tf** is `True` when the corresponding value in **name** or **names** is a dynamic property that exists in **v**.

Data Types: `logical`

See Also

`fieldnames` | `isprop`

Introduced in R2012a

ismap

True for axes with map projection

Syntax

```
mflag = ismap  
mflag = ismap(hndl)  
[mflag,msg] = ismap(hndl)
```

Description

`mflag = ismap` returns a 1 if the current axes is a map axes, and 0 otherwise.

`mflag = ismap(hndl)` specifies the handle of the axes to be tested.

`[mflag,msg] = ismap(hndl)` returns the character vector `msg` if the axes is not a map axes, specifying why not.

The `ismap` function tests an axes object to determine whether it is a map axes.

See Also

`gcm` | `ismapped`

Introduced before R2006a

ismapped

True, if object is projected on map axes

Syntax

```
mflag = ismapped  
mflag = ismapped(hndl)  
[mflag,msg] = ismapped(hndl)
```

Description

`mflag = ismapped` returns a 1 if the current object is projected on a map axes, and 0 otherwise.

`mflag = ismapped(hndl)` specifies the handle of the object to be tested.

`[mflag,msg] = ismapped(hndl)` returns the character vector `msg` if the axes is not projected on a map axes, specifying why not.

The `ismapped` function tests an object to determine whether it is projected on map axes.

See Also

`gcm` | `ismap`

Introduced before R2006a

map.geodesy.IsometricLatitudeConverter

Convert between geodetic and isometric latitudes

Description

An `IsometricLatitudeConverter` object provides conversion methods between geodetic and isometric latitudes for an ellipsoid with a given eccentricity.

The isometric latitude is a nonlinear function of the geodetic latitude that is directly proportional to the spacing of parallels, relative to the Equator, in an ellipsoidal Mercator projection. It is a dimensionless quantity and, unlike other types of auxiliary latitude, the isometric latitude is not angle-valued. It equals `Inf` at the north pole and `-Inf` at the south pole.

Creation

Syntax

```
converter = map.geodesy.IsometricLatitudeConverter  
converter = map.geodesy.IsometricLatitudeConverter(spheroid)
```

Description

`converter = map.geodesy.IsometricLatitudeConverter` returns an `IsometricLatitudeConverter` object for a sphere and sets the `Eccentricity` property to `0`.

`converter = map.geodesy.IsometricLatitudeConverter(spheroid)` returns an isometric latitude converter object and sets the `Eccentricity` property to match the specified spheroid object.

Input Arguments

spheroid — Reference spheroid

referenceEllipsoid | oblateSpheroid | referenceSphere

Reference spheroid, specified as a referenceEllipsoid, oblateSpheroid, or referenceSphere object. To create a spheroid object, use the creation function specific to the object, or the wgs84Ellipsoid function.

Example: spheroid = referenceEllipsoid('GRS 80');

Properties

Eccentricity — Ellipsoid eccentricity

0 | numeric scalar

Ellipsoid eccentricity, specified as a numeric scalar. Eccentricity is in the interval [0, 0.5]. Eccentricities larger than 0.5 are possible in theory, but do not occur in practice and are not supported.

Data Types: double

Object Functions

forward Convert geodetic latitude to authalic, conformal, isometric, or rectifying latitude

inverse Convert authalic, conformal, isometric, or rectifying latitude to geodetic latitude

Examples

Create an Isometric Latitude Converter Object and Set Property

```
grs80 = referenceEllipsoid('GRS 80');
```

```
conv1 = map.geodesy.IsometricLatitudeConverter;  
conv1.Eccentricity = grs80.Eccentricity
```

```
conv1 =  
  IsometricLatitudeConverter with properties:  
    Eccentricity: 0.0818
```

Create an Isometric Latitude Converter Object Specifying Spheroid

```
grs80 = referenceEllipsoid('GRS 80');  
conv2 = map.geodesy.IsometricLatitudeConverter(grs80)  
conv2 =  
  IsometricLatitudeConverter with properties:  
    Eccentricity: 0.0818
```

See Also

Functions

[geocentricLatitude](#) | [parametricLatitude](#)

Objects

[AuthalicLatitudeConverter](#) | [ConformalLatitudeConverter](#) | [RectifyingLatitudeConverter](#)

Introduced in R2013a

ispolycw

True if polygon vertices are in clockwise order

Syntax

```
tf = ispolycw(x, y)
```

Description

`tf = ispolycw(x, y)` returns true if the polygonal contour vertices represented by `x` and `y` are ordered in the clockwise direction. `x` and `y` are numeric vectors with the same number of elements.

Alternatively, `x` and `y` can contain multiple contours, either in NaN-separated vector form or in cell array form. In that case, `ispolycw` returns a logical array containing one true or false value per contour.

`ispolycw` always returns true for polygonal contours containing two or fewer vertices.

Vertex ordering is not well defined for self-intersecting polygonal contours. For such contours, `ispolycw` returns a result based on the order of vertices immediately before and after the left-most of the lowest vertices. In other words, of the vertices with the lowest `y` value, find the vertex with the lowest `x` value. For a few special cases of self-intersecting contours, the vertex ordering cannot be determined using only the left-most of the lowest vertices; for these cases, `ispolycw` uses a signed area test to determine the ordering.

Class Support

`x` and `y` may be any numeric class.

Examples

Orientation of a square:

```
x = [0 1 1 0 0];  
y = [0 0 1 1 0];  
ispolycw(x, y)           % Returns 0  
ispolycw(fliplr(x), fliplr(y)) % Returns 1
```

See Also

[poly2ccw](#) | [poly2cw](#) | [polyshape](#)

Introduced before R2006a

isprop

Determine if property exists in geographic or planar vector

Syntax

```
tf = isprop(v,name)
tf = isprop(v,names)
```

Description

`tf = isprop(v,name)` determines whether the value specified by `name` is a property in geographic or planar vector `v`.

`tf = isprop(v,names)` determines whether each value specified by `names` is a property in `v`.

Examples

Check If a Single Property Exists in Geoshape Vector

Create a geoshape vector.

```
s = geoshape(-33.961, 18.484, 'Name', 'Cape Town');
```

Check if Latitude and Name are properties in the geoshape vector.

```
isprop(s, 'Latitude')
```

```
ans = logical
      1
```

```
isprop(s, 'Name')
```



```
ans = logical
     1
```

Both Latitude and Name are properties in the geoshape vector.

Check If Multiple Properties Exist in a Mappoint Vector

Create a mappoint vector.

```
mp = mappoint(-33.961, 18.484, 'Name', 'Cape Town')
```

```
mp =
  1x1 mappoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  X: -33.9610
  Y: 18.4840
  Name: 'Cape Town'
```

Check if a group of properties exist in the mappoint vector.

```
tf = isprop(mp, {'X','x','Latitude','Name'})
```

```
tf = 1x4 logical array
```

```
     1     0     0     1
```

The first and last elements of `tf` are 1 (true) because the properties `X` and `Name` exist in the mappoint vector. The second and third elements of `tf` are 0 (false) because the properties `x` and `Latitude` do not exist in the mappoint vector. Property names are case-sensitive.

Input Arguments

v — Geographic or planar vector

geopoint, geoshape, mappoint, or mapshape object

Geographic or planar vector, specified as a `geopoint`, `geoshape`, `mappoint`, or `mapshape` object.

name — Name of single property

character vector

Name of a single property, specified as a character vector.

names — Name of multiple properties

cell array of character vectors

Name of multiple properties, specified as a cell array of character vectors.

Output Arguments

tf — Flag indicating the property exists in the geographic or planar vector

logical scalar or vector

Flag indicating the property exists in the geographic or planar vector, returned as a logical scalar or vector. Each element of `tf` is `True` when the corresponding value in `name` or `names` is a property that exists in `v`.

Data Types: `logical`

See Also

`isfield` | `properties`

Introduced in R2012a

isShapeMultipart

True if polygon or line has multiple parts

Syntax

```
tf = isShapeMultipart(xdata, ydata)
```

Description

`tf = isShapeMultipart(xdata, ydata)` returns 1 (true) if the polygon or line shape specified by `xdata` and `ydata` consists of multiple NaN-separated parts (i.e. has inner or multiple polygon rings or multiple line segments). The coordinate arrays `xdata` and `ydata` must match in size and have identical NaN locations.

Examples

Check If Datasets Are Multipart

Create a simple data set and check if it's multipart. If a data set contains NaN separators, `isShapeMultipart` returns 1, otherwise 0.

```
sample_xdata = [0 0 1];  
sample_ydata = [0 1 0];  
isShapeMultipart(sample_xdata, sample_ydata)
```

```
ans = logical  
     0
```

Create simple multipart data sets.

```
multi_xdata = [0 0 1 NaN 2 2 3 3];  
multi_ydata = [0 1 0 NaN 2 3 3 2];  
isShapeMultipart(multi_xdata, multi_ydata)
```

```
ans = logical
      1
```

Check a real data set.

```
load coastlines
isShapeMultipart(coastlat, coastlon)
```

```
ans = logical
      1
```

Check the data in a shapefile.

```
S = shaperead('concord_hydro_area');
isShapeMultipart(S(1).X, S(1).Y)
```

```
ans = logical
      0
```

Check another dataset in the shapefile.

```
isShapeMultipart(S(14).X, S(14).Y)
```

```
ans = logical
      1
```

See Also

`polysplit`

Introduced in R2006a

km2deg

Convert spherical distance from kilometers to degrees

Syntax

```
deg = km2deg(km)
deg = km2deg(km, radius)
deg = km2deg(km, sphere)
```

Description

`deg = km2deg(km)` converts distances from kilometers to degrees, as measured along a great circle on a sphere with a radius of 6371 km, the mean radius of the Earth.

`deg = km2deg(km, radius)` converts distances from kilometers to degrees, as measured along a great circle on a sphere having the specified `radius`.

`deg = km2deg(km, sphere)` converts distances from kilometers to degrees, as measured along a great circle on a sphere approximating an object in the Solar System.

Examples

Convert Kilometers to Degrees

Two cities are 340 km apart. How many degrees of arc is that?

```
deg = km2deg(340)
```

```
deg =
  3.0577
```

How many degrees would it be if the cities were on Mars?

```
deg = km2deg(340, 'mars')
```

```
deg =  
    5.7465
```

Input Arguments

km — Distance in kilometers

numeric array

Distance in kilometers, specified as a numeric array.

Data Types: `single` | `double`

radius — Radius

6371 (default) | numeric scalar

Radius of sphere in units of kilometers, specified as a numeric scalar.

sphere — Sphere

'sun' | 'moon' | 'mercury' | 'venus' | 'earth' | ...

Sphere approximating an object in the Solar System, specified as one of the following values: 'sun', 'moon', 'mercury', 'venus', 'earth', 'mars', 'jupiter', 'saturn', 'uranus', 'neptune', or 'pluto'. The value of `sphere` is case-insensitive.

Output Arguments

deg — Distance in degrees

numeric array

Distance in degrees, returned as a numeric array.

Data Types: `single` | `double`

See Also

`deg2km` | `deg2rad` | `km2rad` | `nm2deg` | `rad2deg` | `sm2deg`

Introduced in R2007a

km2nm

Convert kilometers to nautical miles

Syntax

`nm = km2nm(km)`

Description

`nm = km2nm(km)` converts distances from kilometers to nautical miles.

See Also

`deg2km` | `deg2nm` | `deg2sm` | `deg2sm` | `km2deg` | `km2rad` | `nm2deg` | `nm2rad` | `rad2km` | `rad2nm` | `rad2sm` | `sm2deg` | `sm2rad`

Introduced in R2007a

km2rad

Convert spherical distance from kilometers to radians

Syntax

```
rad = km2rad(km)
rad = km2rad(km, radius)
rad = km2rad(km, sphere)
```

Description

`rad = km2rad(km)` converts distances from kilometers to radians, as measured along a great circle on a sphere with a radius of 6371 km, the mean radius of the Earth.

`rad = km2rad(km, radius)` converts distances from kilometers to radians, as measured along a great circle on a sphere having the specified radius.

`rad = km2rad(km, sphere)` converts distances from kilometers to radians, as measured along a great circle on a sphere approximating an object in the Solar System.

Examples

Convert Kilometers to Radians

How many radians does 1,000 km span on the Earth and on the Moon?

```
rad = km2rad(1000)
```

```
rad =
  0.1570
```

```
rad = km2rad(1000, 'moon')
```

```
rad =
  0.5754
```


Input Arguments

km — Distance in kilometers

numeric array

Distance in kilometers, specified as a numeric array.

Data Types: `single` | `double`

radius — Radius

6371 (default) | numeric scalar

Radius of sphere in units of kilometers, specified as a numeric scalar.

sphere — Sphere

'sun' | 'moon' | 'mercury' | 'venus' | 'earth' | ...

Sphere approximating an object in the Solar System, specified as one of the following values: 'sun', 'moon', 'mercury', 'venus', 'earth', 'mars', 'jupiter', 'saturn', 'uranus', 'neptune', or 'pluto'. The value of sphere is case-insensitive.

Output Arguments

rad — Distance in radians

numeric array

Distance in radians, returned as a numeric array.

Data Types: `single` | `double`

See Also

`deg2rad` | `km2deg` | `nm2rad` | `rad2deg` | `rad2km` | `sm2rad`

Introduced in R2007a

km2sm

Convert kilometers to statute miles

Syntax

```
sm = km2sm(km)
```

Description

`sm = km2sm(km)` converts distances from kilometers to statute miles.

Examples

How many statute miles is a 10k run?

```
sm = km2sm(10)
```

```
sm =  
    6.2137
```

See Also

[deg2km](#) | [deg2nm](#) | [deg2sm](#) | [deg2sm](#) | [km2deg](#) | [km2rad](#) | [nm2deg](#) | [nm2rad](#) | [rad2km](#) | [rad2nm](#) | [rad2sm](#) | [sm2deg](#) | [sm2rad](#)

Introduced in R2007a

kmlwrite

Write geographic data to KML file

Note The following syntaxes, while still supported, are not recommended. Use `kmlwritepoint` instead.

- `kmlwrite(filename,lat,lon)`
 - `kmlwrite(filename,lat,lon,alt)`
-

Syntax

```
kmlwrite(filename,S)
kmlwrite(filename,address)
kmlwrite( ____,Name,Value)
```

Description

`kmlwrite(filename,S)` writes the geographic point, line, or polygon data stored in `S` to the file specified by `filename` in Keyhole Markup Language (KML) format. `S` is a geopoint vector, a geoshape vector, or geostruct. `kmlwrite` creates a KML Placemark in the file and populates the tags in the placemark with the data in `S`.

`kmlwrite(filename,address)` writes `address` to the file specified by `filename` in KML format. `address` is a string scalar or character vector containing freeform address data, that can include street, city, state, country, and/or postal code. To specify multiple addresses, use a cell array of character vectors or string scalars. `kmlwrite` creates a KML Placemark in the file, setting the value of the address tag. An address is an alternative way to specify a point, instead of using latitude and longitude.

`kmlwrite(____,Name,Value)` specifies name-value pairs that set additional KML feature properties. Parameter names can be abbreviated and are case-insensitive.

Examples

Write Point Data to KML File Using `geopoint` Vector

Return point data in `geopoint` vector.

```
placenames = gpxread('boston_placenames');
```

Define the name of the KML file you want to create.

```
filename = 'Boston_Placenames.kml';
```

Define the colors you want to use with the point data.

```
colors = jet(length(placenames));
```

Write the point data to the file, using optional parameters to specify names for the points and define the colors used for the icons.

```
kmlwrite(filename, placenames, 'Name', placenames.Name, 'Color', colors );
```

Write Line Data to KML File Using `geoshape` Vector

Read line features into a `geoshape` vector.

```
tracks = gpxread('sample_tracks', 'Index', 1:2);
```

Define the name of the KML file you want to create.

```
filename = 'tracks.kml';
```

Write the line data to the file, using several optional parameters to specify the color and width of the lines, and their names and descriptions.

```
colors = {'red', 'green'};  
description = tracks.Metadata.Name;  
name = {'track1', 'track2'};
```

```
kmlwrite(filename, tracks, 'Color', colors, 'LineWidth', 2, ...  
        'Description', description, 'Name', name);
```

Write Geographic Data to KML File Using geestruct

Read geographic data (locations of major European cities) from a shape file, including the names of the cities. This returns a structure.

```
latlim = [ 30; 75];  
lonlim = [-25; 45];  
cities = shaperead('worldcities.shp','UseGeoCoords', true, ...  
                  'BoundingBox', [lonlim, latlim]);
```

Convert the structure to a geopoint vector.

```
cities = geopoint(cities);
```

Define the name of the KML file you want to create.

```
filename = 'European_Cities.kml';
```

Write the geographic data to a KML file. Use the optional Name parameter to include the names of the cities in the placemarks. Remove the default Description table.

```
kmlwrite(filename, cities, 'Name', cities.Name, 'Description', {});
```

Write Unstructured Address to KML File

Create a cell array of unstructured addresses (the names of several Australian cities).

```
address = {'Perth, Australia', ...  
          'Melbourne, Australia', ...  
          'Sydney, Australia'};
```

Define the name of the KML file you want to create.

```
filename = 'Australian_Cities.kml';
```

Write the unstructured address data to a KML file, using the optional Name parameter to include the names of the cities in the placemarks.

```
kmlwrite(filename, address, 'Name', address);
```

Write Polygon Data to KML File Using geoshape Vector

Read polygon data from file, returned in a structure.

```
S = shaperead('usastatelo','UseGeoCoords',true);
```

Convert the structure to a geoshape vector.

```
S = geoshape(S);
```

Write the polygon data to a KML file, using optional parameters to specify the colors of the polygon faces and edges.

```
filename = 'usastatelo.kml';  
colors = polcmap(length(S));  
kmlwrite(filename,S,'Name',S.Name,'FaceColor',colors,'EdgeColor','k')
```

Input Arguments

filename — Name of output file

character vector | string scalar

Name of output file, specified as a string scalar or character vector. `kmlwrite` writes the file in the current folder, unless you specify a full or relative path name. If the file name includes an extension, it must be `.kml`.

Data Types: `char` | `string`

S — Geographic features to write to file

geopoint vector, geoshape vector, or geostruct

Geographic features to write to file, specified as a geopoint vector, a geoshape vector, or geostruct. The attribute fields of `S` appear as a table in the Description tag of the Placemark for each element of `S`. The attribute fields appear in the table in the same order as they occur in `S`.

- If `S` is a geoshape vector, the `Geometry` field identifies the type of the data: `'point'`, `'line'`, or `'polygon'`.

- If `S` is a geospatial structure with `X` and `Y` fields, `kmlwrite` returns an error.
- If `S` contains valid altitude data, `kmlwrite` writes the field values to the file as KML altitudes and sets the altitude interpretation to `'relativeToSeaLevel'`. If `S` does not contain altitude data, `kmlwrite` sets the altitude field in the file to `0` and sets the altitude interpretation to `'clampToGround'`. The altitude data can be in a field named either `Elevation`, `Altitude`, or `Height`. If `S` contains fields with more than one of these names, `kmlwrite` issues a warning and ignores the altitude fields.

address — Location of KML placemark

character vector | string scalar | cell array of character vectors

Location of KML placemark, specified as a string scalar, character vector or cell array of character vectors containing freeform address data, such as street, city, state, and postal code. If `address` is a cell array, each cell represents a unique location.

Data Types: `char` | `string` | `cell`

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (`' '`). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

Example: `'Name', 'Point Reyes'`

Name — Label of object displayed in viewer

`'Address N'`, `'Point N'`, `'Line N'`, or `'Polygon N'`, where `N` is the index of the feature. (default) | string scalar | character vector | cell array of character vectors

Label for an object displayed in viewer, specified as a string scalar, character vector, or cell array of character vectors. If you specify a string scalar or character vector, `kmlwrite` applies the name to all objects. If a string vector or cell array of character vectors, you must specify a name for each feature. That is, the cell array must be the same length as `S` or `address`. The following describes the default behavior for various features.

| Feature | Default Name |
|---------|---|
| Address | 'Address N' where <i>N</i> is the index of the feature. |
| Point | 'Point N' where <i>N</i> is the index of the feature. |

| Feature | Default Name |
|------------|---|
| Multipoint | 'Multipoint N' where N is the index of the feature. <code>kmlwrite</code> places the points in the named folder and each point is named 'Point M' where M is the index of the point. |
| Line | 'Line N' where N is the index of the feature. If the line data contains NaN values, <code>kmlwrite</code> places the line segments in a folder named 'Segment M', where M is the line segment number. |
| Polygon | 'Polygon N' where N is the index of the feature. If the polygon vertex list contains multiple outer rings, <code>kmlwrite</code> places each ring in a folder labeled 'Part M', where M is the number for that feature. |

Data Types: `char` | `string` | `cell`

Description — Content to be displayed in the placemark description balloon

`string scalar` | `character vector` | `cell array of character vectors` | `attribute specification`

Content to be displayed in the placemark description balloon, specified as a string scalar or character vector, cell array of character vectors, or an attribute specification. `kmlwrite` uses this data to set the values of the feature description tags. The description appears in the description balloon associated with the feature in Google Earth.

- If you specify a string scalar or character vector, `kmlwrite` applies the description to all objects.
- If you specify a string vector or cell array of character vectors, there must be one label for each feature; that is, it must be the same length as `S` or `address`.

Description elements can be either plain text or tagged with HTML mark up. When in plain text, google Earth applies basic HTML formatting automatically. For example, Google Earth replaces newlines with line break tags and encloses valid URLs in anchor tags to make them hyperlinks. To see examples of HTML tags that are recognized by Google Earth, view <http://earth.google.com>.

If you provide an attribute specification, the attribute fields of `S` display as a table in the description tag of the placemark for each element of `S`, in the order in which the fields appear in the specification. To construct an attribute spec, call `makeattribspec` and then modify the output to remove attributes or change the `Format` field for one or more attributes. The `latitude` and `longitude` coordinates of `S` are not considered to be attributes. If included in an attribute spec, `kmlwrite` ignores them.

Data Types: `char` | `string` | `cell`

Icon — File name of custom icon

defined by viewer (default) | `string` scalar | `character` vector | `cell` array of `character` vectors

File name of custom icon, specified as a `string` scalar, `character` vector or `cell` array of `character` vectors.

- If a `string` scalar or `character` vector, `kmlwrite` applies the value to all icons.
- If a `string` vector or `cell` array of `character` vectors, specify an icon for each feature; that is, the `cell` array must be the same length as `S` or `address`.
- If the `string` scalar or `character` vector is an Internet URL, the URL must include the protocol type.
- If the icon filename is not in the current folder, or in a folder on the MATLAB path, specify a full or relative pathname.

Data Types: `char` | `string` | `cell`

IconScale — Scaling factor for icon

positive numeric scalar or vector

Scaling factor for the icon, specified as a positive numeric scalar or vector.

- If a scalar, `kmlwrite` applies the value to all objects
- If a vector, specify a scale factor for each feature. That is, the `cell` array must be the same length as `S` or `address`.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32`

Color — Color of icons, lines, or the faces and edges of polygons

defined by viewer (default) | MATLAB `ColorSpec`

Color of icons, lines, or the faces and edges of polygons, specified as a MATLAB Color Specification (`ColorSpec`), which can be a `character` vector, `cell` array, or `double` array with values in the range `[0 1]`.

- If a `string` scalar or `character` vector, `kmlwrite` applies the color to all features
- If a `string` vector or `cell` array of `character` vectors, specify a color for each feature. That is, the `cell` array must be the same length as `S` or `address`.

- If a `double` array, specify an M -by-3 array, where M is the same length as `S` or `address`.
- If `S` is a polygon geoshape, you can specify `'none'`, which indicates that the polygon is not filled and has no edge. Also, for polygons, `Color` specifies the color of polygon faces if `FaceColor` is not specified and polygon edges if `EdgeColor` is not specified.

Data Types: `double` | `char` | `cell`

Alpha — Transparency of the icons, lines, or the faces and edges of polygons

1 (fully opaque) (default) | numeric scalar or vector in the range [0 1]

Transparency of the icons, lines, or the faces and edges of polygons, specified as a numeric scalar or vector in the range [0 1]. If a scalar, `kmlwrite` applies the value to all features. If a vector, specify a value for each feature; that is, the vector must be the same length as `S` or `address`. If `S` is a polygon geoshape, `kmlwrite` applies the value to all the polygon faces if `FaceAlpha` is not specified and the polygon edges if `EdgeAlpha` is not specified.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32`

LineWidth — Width of lines and polygon edges in pixels

defined by viewer (default) | positive numeric scalar or vector

Width of lines and polygon edges in pixels, specified as a positive numeric scalar or vector.

- If a scalar, `kmlwrite` applies the value to all polygon edges.
- If a vector, specify a value for each feature. That is, the vector must have the same length as `S`.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32`

FaceColor — Color of polygon faces

defined by viewer (default) | `colorSpec` | `'none'`

Color of polygon edges, specified as a MATLAB Color Specification (`ColorSpec`). A color specification can be a character vector, cell array or character vectors, or a `double` array with values in the range [0 1]. If a character vector, `kmlwrite` applies the value to all faces. If a cell array of character vectors, specify a value for each face. That is, the cell array must be the same length as `S` or `address`. If the value is a numeric array, it is size

M -by-3 where M is the length of S or address. If S is a polygon geoshape, you may specify the value 'none' to indicate that the polygon has no outline.

FaceAlpha — Transparency of polygon faces

1 (fully opaque) (default) | numeric scalar or vector in the range [0 1]

Transparency of polygon faces, specified as a numeric scalar or vector in the range [0 1].

- If a scalar, `kmlwrite` applies the value to all polygon faces.
- If a vector, specify a value for each polygon face; that is, the vector must be the same length as S or address.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32`

EdgeColor — Color of polygon edges

defined by viewer (default) | `colorSpec` | 'none'

Color of polygon edges, specified as a MATLAB Color Specification (`ColorSpec`). A color specification can be a character vector, a cell array of character vectors, or a `double` array with values in the range [0 1].

- If a scalar, `kmlwrite` applies the value to all polygon edges.
- If a vector, specify a value for each polygon edge; that is, the vector must be the same length as S .
- If you specify a `double` array, the size must be M -by-3 where M is the length of S .

The value 'none' indicates that polygons have no edges.

EdgeAlpha — Transparency of the polygon edges

1 (fully opaque) (default) | numeric scalar or vector in the range [0 1]

Transparency of the polygon edges, specified as a numeric scalar or vector.

- If a scalar, `kmlwrite` applies the value to all polygon edges.
- If a vector, specify a value for each polygon edge; that is, the vector must be the same length as S . If you do not specify `EdgeAlpha`, `kmlwrite` uses the value of `Alpha`, if specified. If you do not specify either value, `kmlwrite` uses the default value 1 (fully opaque).

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32`

Extrude — Connect polygons to the ground

`false` (default) | `true` | logical or numeric scalar | logical or numeric vector

Connect polygon to the ground, specified as a logical or numeric scalar, `true` (1) or `false` (0), or vector. If a scalar, the values applies to all polygons. If a vector, specify a value for each polygon; that is, the vector must be the same length as `S` or `address`.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64` | `logical`

CutPolygons — Cut polygon parts

`true` (default) | `false`

Cut polygon parts, specified as a logical or numeric scalar `true` (1) or `false` (0). If `true`, `kmlwrite` cuts polygon parts at the `PolygonCutMeridian` value. If `true`, and the polygon parts require cutting, `kmlwrite` returns an error if the altitude values are nonuniform.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `logical`

PolygonCutMeridian — Meridian where polygon parts are cut

180 (default) | scalar numeric

Meridian where polygon parts are cut, specified as a scalar numeric.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32`

AltitudeMode — Interpretation of altitude values

`'clampToGround'` | `'relativeToGround'` | `'relativeToSeaLevel'`

Interpretation of altitude values, specified as one of the following values:

| Value | Description |
|------------------------------|---|
| <code>'clampToGround'</code> | Ignore altitude values and set the feature on the ground. This is the default interpretation when you do not specify altitude values. |

| Value | Description |
|----------------------|--|
| 'relativeToGround' | Set altitude values relative to the actual ground elevation of a particular feature |
| 'relativeToSeaLevel' | Set altitude values relative to sea level, regardless of the actual elevation values of the terrain beneath the feature. (Named 'absolute' in the KML specification.) This is the default interpretation when you specify altitude values. |

Data Types: char | string

LookAt — Position of virtual camera (eye) relative to object being viewed

geopoint vector

Position of the virtual camera (eye) relative to the object being viewed, specified as a geopoint vector. The fields of the geopoint vector, listed below, define the view. LookAt is limited to looking down at a feature. To tilt the virtual camera to look above the horizon into the sky, use the Camera parameter.

| Property Name | Description | Data Type |
|---------------|--|---|
| Latitude | Latitude of the object the camera is looking at, in degrees | Scalar double, from -90 to 90 |
| Longitude | Longitude of the object the camera is looking at, in degrees | Scalar double, from -180 to 180 |
| Altitude | Altitude of the object the camera is looking at from the Earth's surface, in meters | Scalar numeric |
| Heading | Camera direction (azimuth), in degrees (optional) | Scalar numeric [0 360], default 0 (true North) |
| Tilt | Angle between the direction of the LookAt position and the normal to the surface of the Earth, in degrees (optional) | Scalar numeric [0 90], default 0 (directly above) |
| Range | Distance in meters from the object specified by latitude, longitude, and altitude to the location of the camera. | Scalar numeric, default 0 |

| Property Name | Description | Data Type |
|---------------|--|---|
| AltitudeMode | Interpretation of the camera altitude value (optional) | 'relativeToSeaLevel', 'clampToGround', (default) 'relativeToGround' |

Camera — Position of virtual camera relative to surface of Earth

geopoint vector

Position of virtual camera (eye) relative to Earth's surface, specified as a geopoint vector. The fields of the geopoint vector, listed below, define the view. Camera provides full six degrees of freedom control over the view, so you can position the camera in space and then rotate it around the x-, y-, and z-axes. You can tilt the camera view so that you're looking above the horizon into the sky.

| Property Name | Description | Data Type |
|---------------|--|---|
| Latitude | Latitude of the virtual camera (eye), in degrees | Scalar double, in the range [-90 90] |
| Longitude | Longitude of the virtual camera, in degrees | Scalar double, in the range [-180 180]. |
| Altitude | Distance of the virtual camera from the Earth's surface, in meters | Scalar numeric |
| Heading | Direction (azimuth) in degrees (optional) | Scalar numeric [0 360], default 0 (true North) |
| Tilt | Camera rotation around the X-axis, in degrees (optional) | Scalar numeric [0 180], default 0 (directly above) |
| Roll | Camera rotation in degrees around the Z-axis (optional) | Scalar numeric, in the range [-180 180], default 0 |
| AltitudeMode | Specifies how camera altitude is interpreted (optional) | 'relativeToSeaLevel', 'clampToGround', 'relativeToGround' (default) |

Tips

- You can view KML files with the Google Earth™ browser, which must be installed on your computer.

For Windows, use the `winopen` function:

```
winopen(filename)
```

For Linux, if the filename is a partial path, use the following commands:

```
cmd = 'googleearth ';  
fullfilename = fullfile(pwd, filename);  
system([cmd fullfilename])
```

For Mac, if the filename is a partial path, use the following commands:

```
cmd = 'open -a Google\ Earth '  
fullfilename = fullfile(pwd, filename);  
system([cmd fullfilename])
```

- You can also view KML files with a Google Maps™ browser. The file must be located on a web server that is accessible from the Internet. A private intranet server will not suffice because Google's server must be able to access the URL that you provide. The following is a template for using Google Maps. Replace `your-web-server-path` with a real value.

```
GMAPS_URL = 'http://maps.google.com/maps?q=';  
KML_URL = 'http://your-web-server-path';  
web([GMAPS_URL KML_URL])
```

See Also

`kmlwriteline` | `kmlwritepoint` | `kmlwritepolygon` | `makeattribspec` | `shapewrite`

Introduced in R2007b

kmlwriteline

Write geographic line data to KML file

Syntax

```
kmlwriteline(filename,latitude,longitude)
kmlwriteline(filename,latitude,longitude,altitude)
kmlwriteline( ____,Name,Value)
```

Description

`kmlwriteline(filename,latitude,longitude)` writes the geographic line data specified by `latitude` and `longitude` to the file specified by `filename` in Keyhole Markup Language (KML) format. `kmlwriteline` creates a KML Placemark element for each line, using the latitude and longitude values as the coordinates of the points that define the line. `kmlwriteline` sets the altitude values associated with the line to 0 and sets the altitude interpretation to 'clampToGround'.

`kmlwriteline(filename,latitude,longitude,altitude)` uses the values of `latitude`, `longitude`, and `altitude` to set the coordinates of the points that define the line. When you specify an altitude value, `kmlwriteline` sets the `AltitudeMode` attribute to 'relativeToSeaLevel'.

`kmlwriteline(____,Name,Value)` specifies name-value pairs that set additional KML feature properties. Parameter names can be abbreviated and are case-insensitive.

Examples

Write Line Data to KML File

Load geographic data describing coast lines.

```
load coastlines
```


Define the name of the KML file you want to create.

```
filename = 'coastlines.kml';
```

Write the line data to the file, specifying the color and width of the line.

```
kmlwriteline(filename, coastlat, coastlon, 'Color','black', ...
            'LineWidth', 3);
```

Retrieve GPS Track Log from GPX File and Write Data to KML File

Read the track log from a GPX file. `gpxread` returns the data as a geopoint vector.

```
points = gpxread('sample_tracks');
```

Get the latitude, longitude, and altitude values from the data.

```
lat = points.Latitude;
lon = points.Longitude;
alt = points.Elevation;
```

Define the name of the KML file you want to create.

```
filename = 'track.kml';
```

Write the geographic line data to the file, specifying a description and a name.

```
kmlwriteline(filename,lat, lon, alt, ...
            'Description', points.Metadata.Name, 'Name', 'Track Log');
```

Display Equally Spaced Waypoints Along Two Great Circle Tracks

Read the track data into a geopoint vector.

```
cities = geopoint(shaperead('worldcities','UseGeoCoords',true));
```

Get the latitude, longitude, and altitude values from the data. The example uses London and New York.

```
city1 = 'London';
city2 = 'New York';
pt1 = cities(strcmp(city1,cities.Name));
```

```
pt2 = cities(strcmp(city2,cities.Name));
lat1 = pt1.Latitude;
lon1 = pt1.Longitude;
lat2 = pt2.Latitude;
lon2 = pt2.Longitude;
nlegs = 20;
[lat,lon] = gcwaypts(lat1,lon1,lat2,lon2,nlegs);
midpoint = nlegs/2;
altscale = 5000;
alt = [0:midpoint midpoint-1:-1:0] * altscale;
```

Specify the view using LookAt parameter values.

```
lookLat = 49.155804;
lookLon = -56.698494;
lookAt = geopoint(lookLat, lookLon);
lookAt.Range = 2060400;
lookAt.Heading = 10;
lookAt.Tilt = 70;
```

Write the geographic line data to two KML files, specifying color, width, and view. One track displays altitude values and the other has the track clamped to the ground.

```
width = 4;
filename1 = 'altitudetrack.kml';
kmlwriteline(filename1,lat,lon,alt,'Color','k','LineWidth',width)

filename2 = 'groundtrack.kml';
kmlwriteline(filename2,lat,lon,alt,'Color','w','LineWidth',width, ...
    'LookAt',lookAt,'AltitudeMode','clampToGround')
```

Input Arguments

filename — Name of output file

character vector | string scalar

Name of output file, specified as a string scalar or character vector. `kmlwriteline` creates the file in the current folder, unless you specify a full or relative path name. If the file name includes an extension, it must be `.kml`.

Data Types: `char` | `string`

latitude — Latitudes of points that define the line

vector in the range [-90 90]

Latitudes of points that define the line, specified as a vector in the range [-90 90].

Data Types: single | double

longitude — Longitudes of points that define the line

vector

Longitudes of points that define the line, specified as a vector. Longitude values automatically wrap to the range [-180, 180].

Data Types: single | double

altitude — Altitude of points that define the line

0 (default) | scalar or vector

Altitude of points that define the line, specified as a scalar or vector. Unit of measure is meters.

- If a scalar, kmlwriteline applies the value to each point.
- If a vector, you must specify an altitude value for each point. That is, the vector must have the same length as latitude and longitude.

Data Types: single | double

Name-Value Pair Arguments

Specify optional comma-separated pairs of Name, Value arguments. Name is the argument name and Value is the corresponding value. Name must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as Name1, Value1, ..., NameN, ValueN.

Example: 'Name', 'Point Reyes'

Name — Label of line displayed in viewer

'Line N' where N is the index of the line (default) | string scalar | character vector

Label of line displayed in viewer, specified as a string scalar or character vector.

If the line contains NaN values, `kmlwriteline` places the line segments in a folder labeled 'Line 1'. `kmlwriteline` labels the line segments 'Segment N', where N is the index value of the line segment.

Data Types: `char` | `string`

Description — Content to be displayed in the line description balloon

`string` scalar | `character` vector

Content to be displayed in the line description balloon, specified as a string scalar or character vector. The description appears in the description balloon when the user clicks either the feature name in the Google Earth Places panel or the line in the viewer window.

You can include basic HTML mark up, however, Google Earth applies some HTML formatting automatically. For example, Google Earth replaces newlines with line break tags and encloses valid URLs in anchor tags to make them hyperlinks. To see examples of HTML tags recognized by Google Earth, view <http://earth.google.com>.

Data Types: `char` | `string`

Color — Color of line

defined by viewer (default) | `ColorSpec`

Color of line, specified as a MATLAB Color Specification (`ColorSpec`). You can specify a character vector, scalar cell array, or a numeric vector with values in the range [0 1].

- If you specify a character vector, the value specifies the name of a color (see `ColorSpec`). If you specify 'none', or do not specify this parameter, `kmwriteline` does not include a color specification in the file and leaves the color choice up to the viewer.
- If you specify a cell array, it must be scalar.
- If you specify a numeric array, it must be a 1-by-3 vector of class `double`.

Alpha — Transparency of line

1 (default) | numeric scalar in the range [0 1]

Transparency of line, specified as a numeric scalar in the range [0 1]. The default value, 1, indicates that the line is fully opaque.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64`

LineWidth — Width of line in pixels

defined by viewer (default) | positive numeric scalar

Width of line in pixels, specified as a positive numeric scalar. If you do not specify a width, `kmlwriteline` does not include width information in the file and the viewer defines the line width.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32`

AltitudeMode — Interpretation of altitude values

'`clampToGround`' (default) | '`relativeToGround`' | '`relativeToSeaLevel`'

Interpretation of altitude values, specified as one of the following:

| Value | Description |
|-------------------------------------|--|
| ' <code>clampToGround</code> ' | Ignore altitude values and set the feature on the ground. The default interpretation when you do not specify <code>altitude</code> values. |
| ' <code>relativeToGround</code> ' | Set altitude values relative to the actual ground elevation of a particular feature. |
| ' <code>relativeToSeaLevel</code> ' | Set altitude values relative to sea level, regardless of the actual elevation values of the terrain beneath the feature. The default interpretation when you specify altitude values. Called ' <code>absolute</code> ' in KML terminology. |

Data Types: `char` | `string`

LookAt — Position of virtual camera (eye) relative to object being viewed

geopoint vector

Position of the virtual camera (eye) relative to the object being viewed, specified as a geopoint vector. The fields of the geopoint vector define the view. `LookAt` is limited to looking down at a feature. To tilt the virtual camera to look above the horizon into the sky, use the `Camera` parameter.

| Property Name | Description | Data Type |
|---------------|---|-------------------------------|
| Latitude | Latitude of the line the camera is looking at, in degrees | Scalar double, from -90 to 90 |

| Property Name | Description | Data Type |
|---------------|--|---|
| Longitude | Longitude of the line the camera is looking at, in degrees | Scalar double, from -180 to 180 |
| Altitude | Altitude of the line the camera is looking at from the Earth's surface, in meters | Scalar numeric |
| Heading | Camera direction (azimuth), in degrees (optional) | Scalar numeric [0 360], default 0 (true North) |
| Tilt | Angle between the direction of the LookAt position and the normal to the surface of the Earth, in degrees (optional) | Scalar numeric [0 90], default 0 (directly above) |
| Range | Distance in meters from the point specified by latitude, longitude, and altitude to the position of the camera. | Scalar numeric, default 0 |
| AltitudeMode | Interpretation of the camera altitude value (optional) | 'relativeToSeaLevel', 'clampToGround', (default) 'relativeToGround' |

Camera — Position of virtual camera relative to surface of Earth

geopoint vector

Position of virtual camera (eye) relative to Earth's surface, specified as a geopoint vector. The fields of the geopoint vector, listed below, define the view. Camera provides full 6 degrees of freedom control over the view, so you can position the camera in space and then rotate it around the x-, y-, and z-axes. You can tilt the camera view so that you're looking above the horizon into the sky.

| Property Name | Description | Data Type |
|---------------|--|---|
| Latitude | Latitude of the virtual camera (eye), in degrees | Scalar double, in the range [-90 90] |
| Longitude | Longitude of the virtual camera, in degrees, | Scalar double, in the range [-180 180]. |

| Property Name | Description | Data Type |
|---------------|--|---|
| Altitude | Distance of the virtual camera from the Earth's surface, in meters | Scalar numeric |
| Heading | Direction (azimuth) in degrees (optional) | Scalar numeric [0 360], default 0 (true North) |
| Tilt | Camera rotation around the X-axis, in degrees (optional) | Scalar numeric [0 180], default 0 (directly above) |
| Roll | Camera rotation in degrees around the Z-axis (optional) | Scalar numeric, in the range [-180 180], default 0 |
| AltitudeMode | Specifies how camera altitude is interpreted (optional) | 'relativeToSeaLevel', 'clampToGround', 'relativeToGround' (default) |

Tips

- If you do not see your line, set `AltitudeMode` to `'clampToGround'`. If the line appears, then you may have a problem with your altitude value.
- You can view KML files with the Google Earth browser, which must be installed on your computer.

For Windows, use the `winopen` function:

```
winopen(filename)
```

For Linux, if the file name is a partial path, use the following commands:

```
cmd = 'googleearth ';
fullfilename = fullfile(pwd, filename);
system([cmd fullfilename])
```

For Mac, if the file name is a partial path, use the following commands:

```
cmd = 'open -a Google\ Earth '
fullfilename = fullfile(pwd, filename);
system([cmd fullfilename])
```

- You can also view KML files with a Google Maps browser. The file must be located on a web server that is accessible from the Internet. A private intranet server will not

suffice because Google's server must be able to access the URL that you provide. The following is a template for using Google Maps. Replace `your-web-server-path` with a real value.

```
GMAPS_URL = 'http://maps.google.com/maps?q=' ;  
KML_URL = 'http://your-web-server-path' ;  
web([GMAPS_URL KML_URL])
```

See Also

`kmlwrite` | `kmlwritepoint` | `kmlwritepolygon` | `shapewrite`

Introduced in R2013a

kmlwritepoint

Write geographic point data to KML file

Syntax

```
kmlwritepoint(filename,latitude,longitude)
kmlwritepoint(filename,latitude,longitude,altitude)
kmlwritepoint( ____,Name,Value)
```

Description

`kmlwritepoint(filename,latitude,longitude)` writes the geographic point data specified by `latitude` and `longitude` to the file specified by `filename` in Keyhole Markup Language (KML) format. `kmlwritepoint` creates a KML Placemark element for each point, using the latitude and longitude values as coordinates of the points. `kmlwritepoint` sets the altitude values associated with the points to 0 and sets the altitude interpretation to 'clampToGround'.

`kmlwritepoint(filename,latitude,longitude,altitude)` writes `latitude`, `longitude`, and `altitude` data as point coordinates. When you specify an altitude value, `kmlwritepoint` sets the `AltitudeMode` attribute to 'relativeToSeaLevel'.

`kmlwritepoint(____,Name,Value)` specifies name-value pairs that set additional KML feature properties. Parameter names can be abbreviated and are case-insensitive.

Examples

Write Data to KML File that Includes HTML Format Tags

Define a point by latitude and longitude.

```
lat = 42.299827;
lon = -71.350273;
```

Specify the description text used with the placemark, including HTML tags for formatting.

```
description = sprintf('%s<br>%s</br><br>%s</br>', ...  
    '3 Apple Hill Drive', 'Natick, MA. 01760', ...  
    'https://www.mathworks.com');  
name = 'The MathWorks, Inc.';  
iconDir = fullfile(matlabroot, 'toolbox', 'matlab', 'icons');  
iconFilename = fullfile(iconDir, 'matlabicon.gif');
```

Define the name of the KML file you want to create.

```
filename = 'MathWorks.kml';
```

Write the data to a KML file, using the `Description` parameter to include the names of the cities in the placemarks.

```
kmlwritepoint(filename, lat, lon, ...  
    'Description', description, 'Name', name, 'Icon', iconFilename);
```

Retrieve Point Data from Shape File and Write Data to KML File

Read the locations of major cities from a shape file into a geostruct.

```
latlim = [ 30; 75];  
lonlim = [-25; 45];  
cities = shaperead('worldcities.shp', 'UseGeoCoords', true, ...  
    'BoundingBox', [lonlim, latlim]);
```

Get the latitudes, longitudes, and names of the cities from the geostruct.

```
lat = [cities.Lat];  
lon = [cities.Lon];  
name = {cities.Name};
```

Define the name of the KML file you want to create.

```
filename = 'European_Cities.kml';
```

Write the geographic data to the file, specifying the names of the cities and the size of the icon.

```
kmlwritepoint(filename, lat, lon, 'Name', name, 'IconScale', 2);
```

Write Point Data to KML File Using Camera to Specify View

Create a geopoint object to specify the viewing options available through the Camera parameter. The example sets up a view of the Washington Monument in Washington D.C.

```
camlat = 38.889301;  
camlon = -77.039731;  
camera = geopoint(camlat,camlon);  
camera.Altitude = 500;  
camera.Heading = 90;  
camera.Tilt = 45;  
camera.Roll = 0;  
name = 'Camera ground location';
```

Define the name of the KML file you want to create.

```
filename = 'WashingtonMonument.kml';
```

Write the point data to the file with the view specification. Place a marker at the ground location of the camera.

```
lat = camera.Latitude;  
lon = camera.Longitude;  
kmlwritepoint(filename,lat,lon,'Camera',camera,'Name',name);
```

Write Point Data to KML File Using LookAt to Specify View

Specify the latitude, longitude, and altitude values that define a point. In this example, the location is the Machu Picchu ruins in Peru.

```
lat = -13.163111;  
lon = -72.544945;  
alt = 2430;
```

Create a geopoint object to specify the viewing options available through the LookAt parameter.

```
lookAt = geopoint(lat,lon);  
lookAt.Range = 1500;
```

```
lookAt.Heading = 260;  
lookAt.Tilt = 67;  
name = 'LookAt location parameters';
```

Define the name of the KML file you want to create.

```
filename = 'Machu_Picchu.kml';
```

Write the point data to the file, using the LookAt parameter to specify the view.

```
kmlwritepoint(filename,lat,lon,alt,'Name',name,'LookAt',lookAt)
```

Use Camera Parameter to Specify View

Specify the latitude and longitude values that define the point that you want to view. In this example, the location is Mount Ranier.

```
lat_rainier = 46.8533;  
lon_rainier = -121.7599;
```

Create a geopoint vector to specify the position of the virtual camera (eye) you will use to view the location using the Camera parameter.

```
myview = geopoint(46.7, -121.7, 'Altitude',2500,'Tilt',85,'Heading',345);
```

Define the name of the KML file you want to create.

```
filename = 'Mt_Ranier.kml';
```

Write the point data to the file, specifying a name and a custom color for the icon.

```
kmlwritepoint(filename,lat_rainier,lon_rainier,'Name','Mt Rainier',...  
             'Color','red','IconScale',2,'Camera',myview)
```

Input Arguments

filename — Name of output file

string scalar | character vector

Name of output file, specified as a string scalar or character vector. `kmlwritepoint` creates the file in the current folder, unless you specify a full or relative path name. If the file name includes an extension, it must be `.kml`.

Data Types: `char` | `string`

latitude — Latitudes of points

vector in the range [-90 90]

Latitudes of points, specified as a vector in the range [-90 90].

Data Types: `single` | `double`

longitude — Longitudes of points

vector

Longitudes of points, specified as a vector. Longitude values automatically wrap to the range [-180 180], in compliance with the KML specification.

Data Types: `single` | `double`

altitude — Altitude of points in meters

0 (default) | scalar or vector

Altitude of points in meters, specified as a scalar or vector.

- If a scalar, `kmlwritepoint` applies the value to each point.
- If a vector, you must specify an altitude value for each point. That is, the vector must have the same length as `latitude` and `longitude`.

Data Types: `single` | `double`

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

Example: `kmlwritepoint(filename, lat, lon, 'Name', 'Point Reyes', 'IconScale', 2);`

Name — Label of point displayed in viewer

'Point N' where N is the index of the point (default) | string scalar | string array | character vector | cell array of character vectors

Label of point displayed in viewer, specified as a string scalar or character vector or cell array of character vectors.

- If a string scalar or character vector, `kmlwritepoint` applies the name to all points.
- If a string array or cell array of character vectors, you must include a label for each point; that is, the cell array must have the same length as `latitude` and `longitude`.

Data Types: `char` | `string` | `cell`

Description — Content to be displayed in the point description balloon

string scalar | character vector | cell array of character vectors

Content to be displayed in the point description balloon, specified as a string scalar or character vector or a cell array of character vectors. The content appears in the description balloon when you click either the feature name in the Google Earth Places panel or the point in the viewer window.

- If a string scalar or character vector, `kmlwritepoint` applies the description to all points.
- If a string array or cell array of character vectors, you must include description information for each point; that is, the cell array must be the same length as `latitude` and `longitude`.

Description elements can be either plain text or marked up with HTML. When it is plain text, Google Earth applies basic formatting, replacing newlines with line break tags and enclosing valid URLs with anchor tags to make them hyperlinks. To see examples of HTML tags that Google Earth recognizes, view <http://earth.google.com>.

Data Types: `char` | `string` | `cell`

Icon — File name of a custom icon

defined by viewer, for example, Google Earth uses an image of a push pin. (default) | string scalar | string array | character vector | cell array of character vectors

File name of a custom icon, specified as a string scalar or character vector or cell array of character vectors.

- If a string scalar or character vector, `kmlwritepoint` uses the icon for all points.

- If a string array or cell array of character vectors, you must specify an icon for each point. That is, the cell array must be the same length as `latitude` and `longitude`.

If the icon filename is not in the current folder, or in a folder on the MATLAB path, you must specify a full or relative pathname. If the filename is an Internet URL, the URL must include the protocol type.

Data Types: `char` | `string` | `cell`

IconScale — Scaling factor for icon

positive numeric scalar or vector

Scaling factor for the icon, specified as a positive numeric scalar or vector.

- If a scalar, `kmlwritepoint` applies the scaling factor to the icon for all points.
- If a vector, you must specify a scaling factor for each icon. That is, the vector must be the same length as `latitude` and `longitude`.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32`

Color — Color of icons

defined by viewer (default) | `ColorSpec`

Color of icons, specified as a MATLAB Color Specification (`ColorSpec`). You can specify a character vector, scalar cell array containing a character vector, or a vector with values in the range `[0 1]`.

- If a character vector, `kmlwritepoint` applies the color to all points. If you specify `'none'`, `kmlwritepoint` does not include a color specification in the file and leaves the color choice up to the viewer.
- If a cell array, you must specify a color for each point. That is, the cell array must be the same length as `latitude` and `longitude`.
- If an array, it must be an M -by-3 array where M is the length of `latitude` and `longitude`.

Alpha — Transparency of the icons

1 (default) | numeric scalar or vector in the range `[0 1]`

Transparency of the icons, specified as a numeric scalar or vector in the range `[0 1]`. The default value, 1, indicates fully opaque.

- If a scalar, `kmlwritepoint` applies the value to all icons.
- If a vector, you must specify a value for each icon. That is, the vector must be the same length as `latitude` and `longitude`.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32`

AltitudeMode — Interpretation of altitude values

`'clampToGround'` | `'relativeToGround'` | `'relativeToSeaLevel'`

Interpretation of altitude values, specified as one of the following values:

| Value | Description |
|-----------------------------------|--|
| <code>'clampToGround'</code> | Ignore altitude values and set the feature on the ground. This is the default interpretation when you do not specify <code>altitude</code> values. |
| <code>'relativeToGround'</code> | Set altitude values relative to the actual ground elevation of a particular feature. |
| <code>'relativeToSeaLevel'</code> | Set altitude values relative to sea level, regardless of the actual elevation values of the terrain beneath the feature. This is the default interpretation when you specify altitude values. Called <code>'absolute'</code> in KML terminology. |

Data Types: `char` | `string`

LookAt — Position of the virtual camera (eye) relative to the object being viewed

`geopoint` vector

Position of the virtual camera (eye) relative to the object being viewed, specified as a `geopoint` vector. The view is defined by the fields of the `geopoint` vector, listed in the table below. `LookAt` is limited to looking down at a feature, you cannot tilt the virtual camera to look above the horizon into the sky. To tilt the virtual camera to look above the horizon into the sky, use the `Camera` parameter.

| Property Name | Description | Data Type |
|---------------|--|---|
| Latitude | Latitude of the point the camera is looking at, in degrees north or south of the Equator (0 degrees) | Scalar double, from -90 to 90 |
| Longitude | Longitude of the point the camera is looking at, in degrees, specifying angular distance relative to the Prime Meridian | Scalar double, in the range [-180 180]. Values west of the Meridian range from -180 to 0 degrees. Values east of the Meridian range from 0 to 180 degrees |
| Altitude | Altitude of the point the camera is looking at from the Earth's surface, in meters | Scalar numeric, default 0 |
| Heading | Camera direction (azimuth), in degrees (optional) | Scalar numeric [0 360], default 0 (true North) |
| Tilt | Angle between the direction of the LookAt position and the normal to the surface of the earth, in degrees (optional) | Scalar numeric [0 90], default: 0, directly above. |
| Range | Distance in meters from the point specified by latitude, longitude, and altitude to the point where the camera is positioned—theLookAt position. | Scalar numeric, default: 0 |
| AltitudeMode | Interpretation of camera altitude value (optional) | 'relativeToSeaLevel', 'clampToGround', (default) 'relativeToGround' |

Camera — Position of the virtual camera relative to the surface of the Earth

geopoint vector

Position of the camera relative to the Earth's surface, specified as a geopoint vector. The fields of the geopoint vector, listed below, define the view.Camera provides full six-degrees-of-freedom control over the view, so you can position the camera in space and

then rotate it around the *X*, *Y*, and *Z* axes. You can tilt the camera view so that you're looking above the horizon into the sky.

| Property Name | Description | Data Type |
|---------------|---|---|
| Latitude | Latitude of the virtual camera (eye), in degrees north or south of the Equator (0 degrees) | Scalar double in the range [-90 90] |
| Longitude | Longitude of the virtual camera, in degrees, specifying angular distance relative to the Prime Meridian | Scalar double, in the range [-180 180]. Values west of the Meridian range from -180 to 0 degrees. Values east of the Meridian range from 0 to 180 degrees |
| Altitude | Distance of the virtual camera from the surface of the Earth, in meters | Scalar numeric |
| Heading | Direction (azimuth) in degrees (optional) | Scalar numeric [0 360], default 0 (true North) |
| Tilt | Camera rotation around the <i>X</i> -axis, in degrees (optional) | Scalar numeric [0 180], default: 0, directly above |
| Roll | Camera rotation in degrees around the <i>Z</i> -axis (optional) | Scalar numeric, in the range [-180 180] default: 0 |
| AltitudeMode | Specifies the interpretation of camera altitude. (optional) | 'relativeToSeaLevel', 'clampToGround' , (default) 'relativeToGround' |

- If a scalar, `kmlwritepoint` applies the value to all the points.
- If a vector, you must include an item for each point; that is, the length must be the same length as `latitude` and `longitude`.

Tips

- You can view KML files with the Google Earth browser, which must be installed on your computer.

For Windows, use the `winopen` function:

```
winopen(filename)
```

For Linux, if the filename is a partial path, use the following commands:

```
cmd = 'googleearth ' ;  
fullfilename = fullfile(pwd, filename);  
system([cmd fullfilename])
```

For Mac, if the filename is a partial path, use the following commands:

```
cmd = 'open -a Google\ Earth ' ;  
fullfilename = fullfile(pwd, filename);  
system([cmd fullfilename])
```

- You can also view KML files with a Google Maps browser. The file must be located on a web server that is accessible from the Internet. A private intranet server will not suffice because Google's server must be able to access the URL that you provide. The following is a template for using Google Maps. Replace your -web-server-path with a real value.

```
GMAPS_URL = 'http://maps.google.com/maps?q=' ;  
KML_URL = 'http://your-web-server-path';  
web([GMAPS_URL KML_URL])
```

See Also

kmlwrite | kmlwriteline | kmlwritepolygon | shapewrite

Introduced in R2013a

kmlwritepolygon

Write geographic polygon to KML file

Syntax

```
kmlwritepolygon(filename, latitude, longitude)
kmlwritepolygon(filename, latitude, longitude, altitude)
kmlwritepolygon( ____, Name, Value)
```

Description

`kmlwritepolygon(filename, latitude, longitude)` writes the geographic latitude and longitude data that define polygon vertices to the file specified by `filename` in Keyhole Markup Language (KML) format. `kmlwritepolygon` creates a KML Placemark element for each polygon. By default, `kmlwritepolygon` sets the altitude value associated with the vertices to 0 and sets the altitude interpretation to 'clampToGround'.

`kmlwritepolygon(filename, latitude, longitude, altitude)` writes the polygon data to a KML file, including altitude values for each vertex. `altitude` can be a scalar value, in which case `kmlwritepolygon` uses it as the value for every vertex. If `altitude` is a vector, you must specify a value for every vertex; that is, `altitude` must be the same length as `latitude` and `longitude`. By default, when you specify altitude values, `kmlwritepolygon` sets the altitude interpretation to 'relativeToSeaLevel'.

`kmlwritepolygon(____, Name, Value)` specifies name-value pairs that set additional KML feature properties. Parameter names can be abbreviated and are not case sensitive.

Examples

Write Coastlines to KML File as Polygon

Load latitude and longitude data that defines the coastlines of the continents.

```
load coastlines
```

Specify the name of output KML file that you want to create.

```
filename = 'coastlines.kml';
```

Write the coastline data to the file as a polygon.

```
kmlwritepolygon(filename, coastlat, coastlon)
```

Create Polygon with Inner Ring

Define the latitude and longitude coordinates of the center of the rings. For this example, the coordinates specify the Eiffel Tower.

```
lat0 = 48.858288;
lon0 = 2.294548;
```

Define the inner radius and the outer radius of two small circles. The examples calls `poly2ccw` to change the direction of the vertex order of the second circle to counter-clockwise. This change of direction is needed to define the space between the two circles as a ring-shaped polygon.

```
outerRadius = .02;
innerRadius = .01;
[lat1, lon1] = scircle1(lat0, lon0, outerRadius);
[lat2, lon2] = scircle1(lat0, lon0, innerRadius);
[lon2, lat2] = poly2ccw(lon2, lat2);
lat = [lat1; NaN; lat2];
lon = [lon1; NaN; lon2];
alt = 500;
```

Specify name of output KML file and write the data to the file.

```
filename = 'EiffelTower.kml';
kmlwritepolygon(filename, lat, lon, alt, ...
    'EdgeColor', 'g', 'FaceColor', 'c', 'FaceAlpha', .5)
```

Create Polygon That Spans the 180 Degree Meridian

Specify latitude and longitude coordinates that define the vertices of the polygon. For this example, specify longitude values that span the 180 degree meridian.

```
lat = [0 1 1 0 0];  
lon = [179.5 179.5 -179.5 -179.5 179.5];  
h = 5000;  
alt = ones(1,length(lat)) * h;  
filename = 'cross180.kml';  
kmlwritepolygon(filename,lat,lon,alt,'EdgeColor','r','FaceColor','w')
```

By default, the polygon contains a seam at the 180 degree mark. To remove this seam, set `PolygonCutMeridian` to 0.

```
filename = 'noseam.kml';  
kmlwritepolygon(filename,lat,lon,alt,'EdgeColor','r', ...  
    'FaceColor','w','PolygonCutMeridian',0);
```

To display a ramp without a seam, wrap the longitude values to the range [0 360], and set `CutPolygon` to false. Use the `Extrude` parameter to connect the polygon to the ground for better visibility.

```
filename = 'ramp.kml';  
lon360 = wrapTo360(lon);  
altramp = [0 0 h h 0];  
kmlwritepolygon(filename,lat,lon360,altramp,'EdgeColor','r', ...  
    'FaceColor','w','CutPolygons',false,'Extrude',true);
```

Input Arguments

filename — Name of output file

string scalar | character vector

Name of output file, specified as a string scalar or character vector. `kmlwritepolygon` creates the file in the current folder, unless you specify a full or relative path name. If the file name includes an extension, it must be `.kml`.

Data Types: `char` | `string`

latitude — Latitudes of polygon vertices

vector in the range [-90 90]

Latitudes of polygon vertices, specified as a vector in the range [-90 90].

Data Types: `single` | `double`

longitude — Longitude of polygon vertices

vector in the range [-180, 180]

Longitude of polygon vertices, specified as a vector in the range [-180, 180].

Data Types: `single` | `double`

altitude — Altitude of polygon vertices

0 (default) | scalar or vector

Altitude of polygon vertices, specified as a scalar or vector. Unit of measure is meters.

- If a scalar, `kmlwritepolygon` applies the value to each point.
- If a vector, you must specify an altitude value for each vertex. That is, the vector `altitude` must be the same length as `latitude` and `longitude`.

Data Types: `single` | `double`

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

Example:

```
kmlwritepolygon(filename,lat,lon,alt,'EdgeColor','g','FaceColor','c',
'FaceAlpha',.5)
```

Name — Label displayed in the viewer for the polygon

'Polygon 1' (default) | string scalar | character vector

Label displayed in the viewer for the polygon, specified as the comma-separated pair consisting of 'Name' and a string scalar or character vector. If the vertex list contains multiple outer rings, `kmlwritepolygon` creates a folder with the value of `Name` and each outer ring labeled 'Part N' where N varies from 1 to the number of outer rings.

Data Types: `char` | `string`

Description — Content to be displayed in the polygon description balloon

character vector | string scalar

Content to be displayed in the polygon description balloon, specified as the comma-separated pair consisting of 'Description' and a string scalar or character vector. The content appears in the description balloon when you click either the feature name in the Google Earth Places panel or the polygon in the viewer window.

Description elements can be either plain text or HTML markup. When it is plain text, Google Earth applies basic formatting, replacing newlines with line break tags and enclosing valid URLs with anchor tags to make them hyperlinks. To see examples of HTML tags that Google Earth recognizes, see <http://earth.google.com>.

Data Types: char | string

FaceColor — Color of the polygon face

defined by viewer (default) | ColorSpec

Color of the polygon face, specified as the comma-separated pair consisting of 'FaceColor' and a MATLAB Color Specification (ColorSpec). You can specify a character vector, scalar cell array containing a character vector, or a 1-by-3 vector of doubles with values in the range [0 1]. To create a polygon that is not filled, specify the value 'none'.

Data Types: double | char | cell

FaceAlpha — Transparency of the polygon face

1 (default) | numeric scalar in the range [0 1]

Transparency of the polygon face, specified as the comma-separated pair consisting of 'FaceAlpha' and a numeric scalar in the range [0 1]. The default value, 1, indicates that the face is fully opaque.

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64

EdgeColor — Color of the polygon edges

white (default) | colorSpec

Color of the polygon edge, specified as the comma-separated pair consisting of 'EdgeColor' and a MATLAB Color Specification (ColorSpec). You can specify a character vector, scalar cell array containing a character vector, or a 1-by-3 vector of doubles with values between 0 and 1. To indicate that the polygon has no outline, specify the value 'none'.

Data Types: double | char | cell

EdgeAlpha — Transparency of polygon edges

1 (default) | numeric scalar in the range [0 1]

Transparency of polygon edge, specified as the comma-separated pair consisting of 'EdgeAlpha' and a numeric scalar in the range [0 1]. The default value, 1, indicates that the edge is fully opaque.

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64

LineWidth — Width of the polygon edge in pixels

determined by viewer (default)

Width of the polygon edge in pixels, specified as the comma-separated pair consisting of 'LineWidth' and a positive numeric scalar.

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64

Extrude — Connect polygon to the ground

false (default) | true

Connect polygon to the ground, specified as the comma-separated pair consisting of 'Extrude' and a logical scalar or numeric value true (1) or false (0).

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64 | logical

CutPolygons — Cut polygon parts

true (default) | false

Cut polygon parts, specified as the comma-separated pair consisting of 'CutPolygons' and a logical scalar or numeric value true (1) or false (0). If true, kmlwritepolygon cuts polygons at the meridian specified by PolygonCutMeridian. kmlwritepolygon returns an error if you set this to true, the polygon parts require cutting, and the altitude values are nonuniform.

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64 | logical

PolygonCutMeridian — Meridian where polygon parts are cut

180 (default) | scalar numeric

Meridian where polygon parts are cut, specified as the comma-separated pair consisting of 'PolygonCutMeridian' and a scalar numeric value.

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64

AltitudeMode — Interpretation of altitude values

'clampToGround' | 'relativeToGround' | 'relativeToSeaLevel'

Interpretation of altitude values, specified as the comma-separated pair consisting of 'AltitudeMode' and any of the following values:

| Value | Meaning |
|----------------------|---|
| 'clampToGround' | Ignore the altitude values and set the feature on the ground. This value is the default interpretation when you do not specify altitude values. |
| 'relativeToGround' | Set altitude values relative to the actual ground elevation of a particular feature. |
| 'relativeToSeaLevel' | Set altitude values relative to sea level, regardless of the actual elevation values of the terrain beneath the feature. This value is the default interpretation when you specify altitude values. In KML terminology, this interpretation is called 'absolute'. |

Data Types: char

LookAt — Position of virtual camera (eye) relative to object being viewed

geopoint vector

Position of virtual camera (eye) relative to object being viewed, specified as the comma-separated pair consisting of 'PLookAt' and a geopoint vector. The LookAt parameter defines the virtual camera that views the polygon. The fields of the geopoint vector define the view, outlined in the table below. LookAt can only look down at a feature. To tilt the virtual camera to look above the horizon into the sky, use the Camera parameter.

| Field | Meaning | Value |
|-------------|---|---------------|
| 'Latitude' | Latitude of the point the camera is looking at, in degrees | Scalar double |
| 'Longitude' | Longitude of the point the camera is looking at, in degrees | Scalar double |

| Field | Meaning | Value |
|-----------------|--|---|
| 'Altitude' | Altitude of the point the camera is looking at, in meters (optional) | Scalar numeric default: 0 |
| 'Heading' | Camera direction (azimuth), in degrees (optional) | Scalar numeric [0 360] default 0 |
| 'Tilt' | Angle between the direction of the LookAt position and the normal to the surface of the Earth (optional) | Scalar numeric [0 90] default: 0 |
| 'Range' | Distance in meters from the point to the LookAt position | Scalar numeric |
| 'Altitude Mode' | Specifies how the altitude is interpreted for the LookAt point (optional) | 'relativeToSeaLevel', 'clampToGround', (default), 'relativeToGround' |

Camera — Position and viewing direction of the virtual camera relative to the Earth's surface

geopoint vector

Position and viewing direction of the camera relative to the Earth's surface, specified as the comma-separated pair consisting of 'Camera' and a geopoint vector. The vector contains the following fields. The camera value provides full six-degrees-of-freedom control over the view, so you can position the camera in space and then rotate it around the X, Y, and Z axes. Most importantly, you can tilt the camera view to look above the horizon into the sky.

| Field | Meaning | Value |
|-------------|--|---------------------------|
| 'Latitude' | Latitude of the eye point (virtual camera), specified in degrees | Scalar double |
| 'Longitude' | Longitude of the eye point (virtual camera), specified in degrees | Scalar double |
| 'Altitude' | Distance of the camera from the Earth's surface, specified in meters | Scalar numeric default: 0 |

| Field | Meaning | Value |
|-----------------|--|--|
| 'Heading' | Camera direction (azimuth) in degrees (Optional) | Scalar numeric [0 360] default 0 |
| 'Tilt' | Camera rotation around the X axis, specified in degrees (Optional) | Scalar numeric [0 180] default: 0 |
| 'Roll' | Camera rotation around the Z axis, specified in degrees (Optional) | Scalar numeric, default: 0 |
| 'Altitude Mode' | Specifies how <code>kmlwritepolygon</code> interprets camera altitude values. (Optional) | 'relativeToSeaLevel', 'clampToGround', (default), 'relativeToGround' |

See Also

`kmlwrite` | `kmlwriteline` | `kmlwritepoint` | `shapewrite`

Introduced in R2016a

latitudeToIntrinsicY

Package: map.rasterref

Convert from latitude to intrinsic y coordinates

Syntax

```
yIntrinsic = latitudeToIntrinsicY(R, lat)
```

Description

`yIntrinsic = latitudeToIntrinsicY(R, lat)` returns the y-coordinate in the intrinsic coordinate system corresponding to latitude `lat` in the geographic coordinate system, based on the relationship defined by geographic raster `R`.

Input Arguments

R — Geographic raster

GeographicCellsReference or GeographicPostingsReference object

Geographic raster, specified as a GeographicCellsReference or GeographicPostingsReference object.

lat — Latitude coordinates

numeric array

Latitude coordinates, specified as a numeric array. Valid values of `lat` are in the range [-90, 90] degrees. `lat` coordinates can be outside the bounds of the raster `R`.

Data Types: `single` | `double`

Output Arguments

yIntrinsic — y-coordinates in intrinsic coordinate system

numeric array

y-coordinates in intrinsic coordinate system, returned as a numeric array. `yIntrinsic` is the same size as `lat`.

When a point has valid latitude outside the bounds of raster `R`, `yIntrinsic(k)` is extrapolated in the intrinsic coordinate system. When `lat(k)` is outside the range `[-90, 90]` degrees, or has a value of `NaN`, the corresponding value `yIntrinsic(k)` is set to `NaN`.

Data Types: `double`

See Also

`geographicToIntrinsic` | `intrinsicYToLatitude` | `longitudeToIntrinsicX`

Introduced in R2013b

latlon2pix

Convert latitude-longitude coordinates to pixel coordinates

Syntax

```
[row, col ] = latlon2pix(R,lat,lon)
```

Description

`[row, col] = latlon2pix(R,lat,lon)` calculates pixel coordinates `row`, `col` from latitude-longitude coordinates `lat`, `lon`. `R` is either a 3-by-2 referencing matrix that transforms intrinsic pixel coordinates to geographic coordinates, or a geographic raster reference object. `lat` and `lon` are vectors or arrays of matching size. The outputs `row` and `col` have the same size as `lat` and `lon`. `lat` and `lon` must be in degrees.

Longitude wrapping is handled in the following way: Results are invariant under the substitution `lon = lon +/- n * 360` where `n` is an integer. Any point on the Earth that is included in the image or gridded data set corresponding to `r` will yield row/column values between 0.5 and 0.5 + the image height/width, regardless of what longitude convention is used.

Examples

Find the pixel coordinates of the upper left and lower right outer corners of a 2-by-2 degree gridded data set.

```
R = makerefmat(1, 89, 2, 2);
[UL_row, UL_col] = latlon2pix(R, 90, 0)      % Upper left
[LR_row, LR_col] = latlon2pix(R, -90, 360)   % Lower right
[LL_row, LL_col] = latlon2pix(R, -90, 0)     % Lower left
```

Note that in both the 2nd case and 3rd case we get a column value of 0.5, because the left and right edges are on the same meridian and (-90, 360) is the same point as (-90, 0).

See Also

`makerefmat` | `map2pix` | `pix2latlon`

Introduced before R2006a

lcolorbar

Colorbar with text labels

Syntax

```
lcolorbar(labels)
lcolorbar(labels, 'property', value, ...)
hcb = lcolorbar(...)
```

Description

`lcolorbar(labels)` appends text labels to a colorbar. The `labels` input argument is a cell array of character vectors. The colorbar is constructed using the current colormap with the labels applied at the centers of the color bands.

`lcolorbar(labels, 'property', value, ...)` controls the colorbar's properties.

| Property | Description |
|----------------|---|
| Location | Controls the location of the colorbar. Valid values are 'vertical' (the default) or 'horizontal'. |
| TitleString | Text of title. |
| XLabelString | Text of XLabel. |
| YLabelString | Text of YLabel. |
| ZLabelString | Text of ZLabel. |
| ColorAlignment | Controls whether the colorbar labels are centered on the color bands or the color breaks. Valid values are 'center' and 'ends'. |

Other valid property-value pairs are any properties and values that can be applied to the title and labels of the colorbar axes.

`hcb = lcolorbar(...)` returns a handle to the colorbar axes.

Examples

```
figure; colormap(jet(5))
labels = {'apples', 'oranges', 'grapes', 'peaches', 'melons'};
lcolorbar(labels, 'fontweight', 'bold');
```

See Also

Colormap Editor | `contourcmap`

legs

Courses and distances between navigational waypoints

Syntax

```
[course,dist] = legs(lat,lon)
[course,dist] = legs(lat,lon,method)
[course,dist] = legs(pts, ___)
mat = legs( ___ )
```

Description

`[course,dist] = legs(lat,lon)` returns the azimuths (`course`) and distances (`dist`) between navigational waypoints, which are specified by the column vectors `lat` and `lon`.

`[course,dist] = legs(lat,lon,method)` specifies the logic for the leg characteristics. If the `method` is `'rh'` (the default), `course` and `dist` are calculated in a rhumb line sense. If `method` is `'gc'`, great circle calculations are used.

`[course,dist] = legs(pts, ___)` specifies waypoints in a single two-column matrix, `pts`.

`mat = legs(___)` packs up the outputs into a single two-column matrix, `mat`.

This is a navigation function. All angles are in degrees, and all distances are in nautical miles. Track legs are the courses and distances traveled between navigational waypoints.

Examples

Imagine an airplane taking off from Logan International Airport in Boston (42.3°N,71°W) and traveling to LAX in Los Angeles (34°N,118°W). The pilot wants to file a flight plan that takes the plane over O'Hare Airport in Chicago (42°N,88°W) for a navigational update, while maintaining a constant heading on each of the two legs of the trip.

What are those headings and how long are the legs?

```
lat = [42.3; 42; 34];  
long = [-71; -88; -118];  
[course,dist] = legs(lat,long,'rh')
```

```
course =  
    268.6365  
    251.2724  
dist =  
    1.0e+003 *  
    0.7569  
    1.4960
```

Upon takeoff, the plane should proceed on a heading of about 269° for 756 nautical miles, then alter course to 251° for another 1495 miles.

How much farther is it traveling by not following a great circle path between waypoints? Using rhumb lines, it is traveling

```
totalrh = sum(dist)
```

```
totalrh =  
    2.2530e+003
```

For a great circle route,

```
[coursegc,distgc] = legs(lat,long,'gc'); totalgc = sum(distgc)
```

```
totalgc =  
    2.2451e+003
```

The great circle path is less than one-half of one percent shorter.

See Also

[dreckon](#) | [gcwaypts](#) | [navfix](#) | [track](#)

length

Return number of elements in geographic or planar vector

Syntax

```
n = length(v)
```

Description

`n = length(v)` returns the number of elements contained in the geographic or planar vector `v`.

Examples

Find Length of Geopoint Vector

Create a geopoint vector and find its length.

```
load coastlines
p = geopoint(coastlat, coastlon);
length(p)
```

```
ans = 9865
```

```
length(coastlat)
```

```
ans = 9865
```

Input Arguments

v — **Geographic or planar vector**

geopoint, geoshape, mappoint, or mapshape object

Geographic or planar vector, specified as a `geopoint`, `geoshape`, `mappoint`, or `mapshape` object.

Output Arguments

n — Number of elements

nonnegative integer scalar

Number of elements in vector `v`, returned as a nonnegative integer scalar. The result is equivalent to `size(v,1)`.

See Also

`size`

Introduced in R2012a

lightm

Project light objects on map axes

Syntax

```
h = lightm(lat,lon)
h = lightm(lat,lon,PropertyName,PropertyValue,...)
h = lightm(lat,lon,alt)
```

Description

`h = lightm(lat,lon)` projects a light object at the coordinates `lat` and `lon`. The handle, `h`, of the object can be returned.

`h = lightm(lat,lon,PropertyName,PropertyValue,...)` allows the specification of any property name/property value pair supported by the standard MATLAB `light` function.

`h = lightm(lat,lon,alt)` allows the specification of an altitude, `alt`, for the light object. When omitted, the default is an infinite light source altitude.

Examples


Add Light to Map

Load data.

```
load topo
```


Create map.

```
axesm globe; view(120,30)
meshm(topo,topolegend); demcmap(topo)
```



Add light, specifying surface reflectance properties and lighting mode.

```
lightm(0,90,'color','yellow')  
material([.5 .5 1]); lighting gouraud
```

See Also

light

Introduced before R2006a

limitm

Determine latitude and longitude limits of regular data grid

Syntax

```
[latlim,lonlim] = limitm(Z,R)
latlonlim = limitm(Z,R)
```

Description

`[latlim,lonlim] = limitm(Z,R)` computes the latitude and longitude limits of the geographic quadrangle bounding the regular data grid `Z` spatially referenced by `R`. `R` can be a geographic raster reference object, a referencing vector, or a referencing matrix.

If `R` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z)`.

If `R` is a referencing vector, it must be 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If `R` is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to/from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If `R` is a referencing matrix, it must also define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. The output `latlim` is a vector of the form `[southern_limit northern_limit]` and `lonlim` is a vector of the form `[western_limit eastern_limit]`. All angles are in units of degrees.

`latlonlim = limitm(Z,R)` concatenates `latlim` and `lonlim` into a 1-by-4 row vector of the form:

```
[southern_limit northern_limit western_limit eastern_limit]
```

Examples

Use a familiar data grid:

```
load topo
[latlimits,lonlimits] = limitm(topo,topolegend)
```

```
latlimits =
    -90    90
lonlimits =
     0   360
```

The result is expected, because `topo` covers the whole globe.

See Also

`makereformat`

Introduced before R2006a

linecirc

Intersections of circles and lines in Cartesian plane

Syntax

```
[xout,yout] = linecirc(slope,intercpt,centerx,centery,radius)
```

Description

`[xout,yout] = linecirc(slope,intercpt,centerx,centery,radius)` finds the points of intersection given a circle defined by a center and radius in x-y coordinates, and a line defined by slope and y-intercept, or a slope of “inf” and an x-intercept. Two points are returned. When the objects do not intersect, NaNs are returned.

When the line is tangent to the circle, two identical points are returned. All inputs must be scalars.

See Also

`circcirc`

Introduced before R2006a

linem

Project line object on map axes

Syntax

```
h = linem(lat,lon)
h = linem(lat,lon,linetype)
h = linem(lat,lon,PropertyName,PropertyValue,...)
h = linem(lat,lon,z)
```

Description

`h = linem(lat,lon)` displays projected line objects on the current map axes. `lat` and `lon` are the latitude and longitude coordinates, respectively, of the line object to be projected. Note that this ordering is conceptually reversed from the MATLAB `line` function, because the *vertical* (*y*) coordinate comes first. However, the ordering latitude, then longitude, is standard geographic usage. `lat` and `lon` must be the same size and in the `AngleUnits` of the map axes. The object handle for the displayed line can be returned in `h`.

`h = linem(lat,lon,linetype)` where `linetype` is a `linespec` that specifies the line style.

`h = linem(lat,lon,PropertyName,PropertyValue,...)` allows the specification of any number of property name/property value pairs for any properties recognized by the MATLAB `line` function except for `XData`, `YData`, and `ZData`.


`h = linem(lat,lon,z)` displays a line object in three dimensions, where `z` is the same size as `lat` and `lon` and contains the desired altitude data. `z` is independent of `AngleUnits`. If omitted, all points are assigned a `z`-value of 0 by default.

The units of `z` are arbitrary, except when using the `Globe` projection. In the case of `globe`, `z` should have the same units as the radius of the earth or semimajor axis specified in the `'geoid'` (reference ellipsoid) property of the map axes. This implies that when the reference ellipsoid is a unit sphere, the units of `z` are earth radii.

`linem` is the mapping equivalent of the MATLAB `line` function. It is a low-level graphics function for displaying line objects in map projections. Ordinarily, it is not used directly. Use `plotm` or `plot3m` instead.

Examples

```
axesm sinusoid; framem  
linem([15; 0; -45; 15],[-100; 0; 100; 170],'r-')
```



See Also

`line` | `plot3m` | `plotm`

longitudeToIntrinsicX

Package: map.rasterref

Convert from longitude to intrinsic x coordinates

Syntax

```
xIntrinsic = longitudeToIntrinsicX(R,lon)
```

Description

`xIntrinsic = longitudeToIntrinsicX(R,lon)` returns the *x*-coordinate in the intrinsic coordinate system corresponding to longitude `lon` in the geographic coordinate system, based on the relationship defined by geographic raster `R`.

Input Arguments

R — Geographic raster

GeographicCellsReference or GeographicPostingsReference object

Geographic raster, specified as a GeographicCellsReference or GeographicPostingsReference object.

lon — Longitude coordinates

numeric array

Longitude coordinates, specified as a numeric array. `lon` coordinates can be outside the bounds of the raster `R`.

Data Types: single | double

Output Arguments

xIntrinsic — x-coordinates in intrinsic coordinate system

numeric array

x-coordinates in intrinsic coordinate system, returned as a numeric array. `xIntrinsic` is the same size as `lat`.

When `lon(k)` is outside the bounds of raster `R`, `xIntrinsic(k)` is extrapolated in the intrinsic coordinate system. Elements of `lon` with value `NaN` map to `NaN` in `xIntrinsic`.

Data Types: `double`

See Also

`geographicToIntrinsic` | `intrinsicXToLongitude` | `latitudeToIntrinsicY`

Introduced in R2013b

lookAtSpheroid

Line of sight intersection with oblate spheroid


Syntax

```
[lat,lon,slanrange] = lookAtSpheroid(lat0,lon0,h0,az,tilt,spheroid)
```

Description

[lat,lon,slanrange] = lookAtSpheroid(lat0,lon0,h0,az,tilt,spheroid) computes the latitude and longitude (lat and lon) of the first point of intersection of the line-of-sight from a viewpoint in space with the surface of an oblate spheroid. If the line-of-sight does not intersect with the spheroid, lat and lon contain NaNs.

lat0 and lon0 are the geodetic coordinates of the viewpoint on the reference spheroid, spheroid. h0 specifies the geodetic height of the viewpoint in space above the spheroid. The az and tilt arguments specify the direction of the view (line-of-sight) as the azimuth angle, measured clockwise from North, and a tilt angle. The following figure illustrates these measurements.



The optional slanrange output argument returns the (3-D Euclidean) distance from the viewpoint to the intersection. All angles are in degrees.

Examples

Calculate Intersection with Spheroid of View from Geostationary Orbit

Create a reference spheroid. Specify the length unit as kilometers.

```
spheroid = wgs84Ellipsoid('km');
```

Define location of view in space. The units for `h0` match the units of the spheroid (kilometers).

```
lat0 = 0;  
lon0 = -100;  
h0 = 35786;
```

Define the view from space in terms of the azimuth angle and tilt.

```
az = 45;  
tilt = 6;
```

Calculate the point on the spheroid at which the view first intersects with the spheroid. The example also returns the distance in kilometers between the viewpoint in space and the first point of intersection with the spheroid.

```
[lat,lon,slanrange] = lookAtSpheroid(lat0,lon0,h0,az,tilt,spheroid)
```

```
lat = 25.7991
```

```
lon = -71.3039
```

```
slanrange = 3.7328e+04
```

Input Arguments

lat0 — Geodetic latitude of the viewpoint on the spheroid

scalar | vector | matrix | N-D array

Geodetic latitude of the viewpoint on the spheroid, specified as a scalar value, vector, matrix, or N-D array.

Data Types: `single` | `double`

lon0 — Geodetic longitude of the viewpoint on the spheroid

scalar | vector | matrix | N-D array

Geodetic longitude of the viewpoint on the spheroid, specified as a scalar value, vector, matrix, or N-D array.

Data Types: single | double

h0 — Height of the viewpoint in space above the spheroid

scalar | vector | matrix | N-D array

Height of the viewpoint in space above the spheroid, specified as a scalar value, vector, matrix, or N-D array. `h0` must be in units that match the spheroid input.

Data Types: single | double

az — Azimuth angle of view from space

scalar | vector | matrix | N-D array

Azimuth angle of view from space, specified as a scalar value, vector, matrix, or N-D array. Measured in degrees, clockwise from north.

Data Types: single | double

tilt — Tilt angle of view from space

scalar | vector | matrix | N-D array

Tilt angle of view from space, specified as scalar value, vector, matrix, or N-D array. Measured in degrees, relative to a vector pointing downward toward the nadir point. The nadir point is the point on the spheroid directly below the viewpoint, with geodetic coordinates (lat0, lon0, 0). When the tilt is zero (0), the line-of-sight is directed at the nadir point itself. Tilt can be in the range [0 180] but for large angles and all angles greater than or equal to 90 degrees, there is no intersection with the spheroid.

Example:

Data Types: single | double

spheroid — Reference spheroid

referenceEllipsoid | oblateSpheroid | referenceSphere

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. Use the constructor for one of these three classes, or the `wgs84Ellipsoid` function, to construct a spheroid object. You cannot directly pass in the

name of the reference spheroid. Instead, pass the name to `referenceEllipsoid` or `referenceSphere` and use the resulting object.

Output Arguments

lat — Latitude of the first point of intersection with the spheroid

scalar | vector | matrix | N-D array

Latitude of the first point of intersection with the spheroid, returned as a scalar value, vector, matrix, or N-D array. If the line-of-sight does not intersect with the spheroid, `lat` contains NaNs.

lon — Longitude of the first point of intersection with the spheroid

scalar | vector | matrix | N-D array

Longitude of the first point of intersection with the spheroid, returned as a scalar value, vector, matrix, or N-D array. If the line-of-sight does not intersect with the spheroid, `lon` contains NaNs.

sLanrange — Distance from the viewpoint to the first intersection with the spheroid

scalar | vector | matrix | N-D array

Distance from the viewpoint to the intersection with the spheroid, returned as a scalar value, vector, matrix, or N-D array. Units match the `LengthUnit` property of the input spheroid object.

See Also

`geodetic2aer`

Introduced in R2016b

los2

Line-of-sight visibility between two points in terrain

Syntax

```
vis = los2(Z,R,lat1,lon1,lat2,lon2)
vis = los2(Z,R,lat1,lon1,lat2,lon2,alt1)
vis = los2(Z,R,lat1,lon1,lat2,lon2,alt1,alt2)
vis = los2(Z,R,lat1,lon1,lat2,lon2,alt1,alt2,altlopt)
vis = los2(Z,R,lat1,lon1,lat2,lon2,alt1,alt2,altlopt,alt2opt)
vis = los2(Z,R,lat1,lon1,lat2,lon2,alt1,alt2,altlopt, ...
    alt2opt,actualradius)
vis = los2(Z,R,lat1,lon1,lat2,lon2,alt1,alt2,altlopt, ...
    alt2opt,actualradius,effectiveradius)
[vis,visprofile,dist,H,lattrk,lontrk] = los2(...)
los2(...)
```

Description

los2 computes the mutual visibility between two points on a displayed digital elevation map. los2 uses the current object if it is a regular data grid, or the first regular data grid found on the current axes. The grid's `zdata` is used for the profile. The color data is used in the absence of data in `z`. The two points are selected by clicking on the map. The result is displayed in a new figure. Markers indicate visible and obscured points along the profile. The profile is shown in a Cartesian coordinate system with the origin at the observer's location. The displayed `z` coordinate accounts for the elevation of the terrain and the curvature of the body.

`vis = los2(Z,R,lat1,lon1,lat2,lon2)` computes the mutual visibility between pairs of points on a digital elevation map. The elevations are provided as a regular data grid `Z` containing elevations in units of meters. The two points are provided as vectors of latitudes and longitudes in units of degrees. The resulting logical variable `vis` is equal to one when the two points are visible to each other, and zero when the line of sight is obscured by terrain. If any of the input arguments are empty, los2 attempts to gather the data from the current axes. With one or more output arguments, no figures are created and only the data is returned.

R can be a geographic raster reference object, a referencing vector, or a referencing matrix. If R is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z)`.

If R is a referencing vector, it must be a 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If R is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to or from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If R is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. Nearest-neighbor interpolation is used by default. NaN is returned for points outside the grid limits or for which `lat` or `lon` contain NaN. All angles are in units of degrees.

`vis = los2(Z,R,lat1,lon1,lat2,lon2,alt1)` places the first point at the specified altitude in meters above the surface (on a tower, for instance). This is equivalent to putting the point on a tower. If omitted, point 1 is assumed to be on the surface. `alt1` may be either a scalar or a vector with the same length as `lat1`, `lon1`, `lat2`, and `lon2`.

`vis = los2(Z,R,lat1,lon1,lat2,lon2,alt1,alt2)` places both points at a specified altitudes in meters above the surface. `alt2` may be either a scalar or a vector with the same length as `lat1`, `lon1`, `lat2`, and `lon2`. If `alt2` is omitted, point 2 is assumed to be on the surface.

`vis = los2(Z,R,lat1,lon1,lat2,lon2,alt1,alt2,altlopt)` controls the interpretation of `alt1` as either a relative altitude (`altlopt` equals 'AGL', the default) or an absolute altitude (`altlopt` equals 'MSL'). If the altitude option is 'AGL', `alt1` is interpreted as the altitude of point 1 in meters above the terrain ("above ground level"). If `altlopt` is 'MSL', `alt1` is interpreted as altitude above zero ("mean sea level").

`vis = los2(Z,R,lat1,lon1,lat2,lon2,alt1,alt2,altlopt,alt2opt)` controls the interpretation ALT2.

`vis = los2(Z,R,lat1,lon1,lat2,lon2,alt1,alt2,altlopt, ...`

`alt2opt,actualradius)` does the visibility calculation on a sphere with the specified radius. If omitted, the radius of the earth in meters is assumed. The altitudes, elevations and the radius should be in the same units. This calling form is most useful for computations on bodies other than the earth.

`vis = los2(Z,R,lat1,lon1,lat2,lon2,alt1,alt2,altlopt, ... alt2opt,actualradius,effectiveradius)` assumes a larger radius for propagation of the line of sight. This can account for the curvature of the signal path due to refraction in the atmosphere. For example, radio propagation in the atmosphere is commonly treated as straight line propagation on a sphere with 4/3 the radius of the earth. In that case the last two arguments would be `R_e` and `4/3*R_e`, where `R_e` is the radius of the earth. Use `Inf` as the effective radius for flat earth visibility calculations. The altitudes, elevations and radii should be in the same units.

`[vis,visprofile,dist,H,lattrk,lontrk] = los2(...)`, for scalar inputs (`lat1`, `lon1`, etc.), returns vectors of points along the path between the two points. `visprofile` is a logical vector containing `true (logical(1))` where the intermediate points are visible and `false (logical(0))` otherwise. `dist` is the distance along the path (in meters or the units of the radius). `H` contains the terrain profile relative to the vertical datum along the path. `lattrk` and `lontrk` are the latitudes and longitudes of the points along the path. For vector inputs `los2` returns `visprofile`, `dist`, `H`, `lattrk`, and `lontrk` as cell arrays, with one cell per element of `lat1`, `lon1`, etc.

`los2(...)`, with no output arguments, displays the visibility profile between the two points in a new figure.

Examples

Find Elevation Angle of Point 90 Degrees from Observer

Find the elevation angle of a point 90 degrees from an observer assuming that the observer and the target are both 1000 km above the Earth.

```
lat1 = 0;
lon1 = 0;
alt1 = 1000*1000;
lat2 = 0;
lon2 = 90;
alt2 = 1000*1000;
[az, elev, r] = geodetic2aer(lat2,lon2,alt2,lat1,lon1,alt1,referenceEllipsoid('grs 80')

az = 90

elev = -45

r = 1.0434e+07
```


Visually check the result using the `los2` line of sight function. Construct a data grid of zeros to represent the Earth's surface. The `los2` function with no output arguments creates a figure displaying the geometry.

```
Z = zeros(181,361);  
R = georefpostings([-90 90],[-180 180], size(Z))
```

```
R =  
  GeographicPostingsReference with properties:
```


```
    LatitudeLimits: [-90 90]  
    LongitudeLimits: [-180 180]  
    RasterSize: [181 361]  
    RasterInterpretation: 'postings'  
    ColumnsStartFrom: 'south'  
    RowsStartFrom: 'west'  
    SampleSpacingInLatitude: 1  
    SampleSpacingInLongitude: 1  
    RasterExtentInLatitude: 180  
    RasterExtentInLongitude: 360  
    XIntrinsicLimits: [1 361]  
    YIntrinsicLimits: [1 181]  
    CoordinateSystemType: 'geographic'  
    AngleUnit: 'degree'
```

```
los2(Z,R,lat1,lon1,lat2,lon2,alt1,alt1);
```

Determine Line-of-Sight


```
Z = 500*peaks(100);
refvec = [1000 0 0];
[lat1, lon1, lat2, lon2] = deal(-0.027, 0.05, -0.093, 0.042);
los2(Z, refvec, lat1, lon1, lat2, lon2, 100);
```



```

figure;
axesm('globe','geoid',earthRadius('meters'))
meshm(Z, refvec, size(Z), Z); axis tight
camposm(-10,-10,1e6); camupm(0,0)
demcmap('inc', Z, 1000); shading interp; camlight
[vis,visprofile,dist,h,lattrk,lontrk] = ...
los2(Z,refvec,lat1,lon1,lat2,lon2,100);
plot3m(lattrk([1;end]),lontrk([1;end]),...
h([1;end])+[100; 0],'r','linewidth',2)
plotm(lattrk(~visprofile),lontrk(~visprofile),...
h(~visprofile),'r.','markersize',10)
plotm(lattrk(visprofile),lontrk(visprofile),...
h(visprofile),'g.','markersize',10)

```



See Also

`mapprofile` | `viewshed`

Introduced before R2006a

ltln2val

Extract data grid values for specified locations

Syntax

```
val = ltln2val(Z, R, lat, lon)
val = ltln2val(Z, R, lat, lon, method)
```

Description

`val = ltln2val(Z, R, lat, lon)` interpolates a regular data grid `Z` with referencing vector `R` at the points specified by vectors of latitude and longitude, `lat` and `lon`. `R` can be a geographic raster reference object, a referencing vector, or a referencing matrix.

If `R` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z)`.

If `R` is a referencing vector, it must be a 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If `R` is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to or from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If `R` is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. Nearest-neighbor interpolation is used by default. NaN is returned for points outside the grid limits or for which `lat` or `lon` contain NaN. All angles are in units of degrees.

`val = ltln2val(Z, R, lat, lon, method)` where `method` specifies the type of interpolation: 'bilinear' for linear interpolation, 'bicubic' for cubic interpolation, or 'nearest' for nearest neighbor interpolation.

Examples

Find the elevations in `topo` associated with three European cities—Milan, Bern, and Prague (`topo` elevations are in meters):

```
load topo
% The city locations, [Milan Bern Prague]
lats = [45.45; 46.95; 50.1];
longs = [9.2; 7.4; 14.45];
elevations = ltn2val(topo,topolegend,lats,longs)

elevations =
    313
   1660
    297
```

See Also

`findm` | `imbedm`

lv2ecef

Convert local vertical to geocentric (ECEF) coordinates

Note `lv2ecef` will be removed in a future release. Use `enu2ecef` instead. In `enu2ecef`, the latitude and longitude of the local origin are in degrees by default, so the optional `angleUnit` input should be included, with the value `'radians'`.

Syntax

```
[x,y,z] = lv2ecef(xl,yl,zl,phi0,lambda0,h0,ellipsoid)
```

Description

`[x,y,z] = lv2ecef(xl,yl,zl,phi0,lambda0,h0,ellipsoid)` converts arrays `xl`, `yl`, and `zl` in the local vertical coordinate system to arrays `x`, `y`, and `z` in the geocentric coordinate system. The origin of the local vertical system is at geodetic latitude `phi0`, geodetic longitude `lambda0`, and ellipsoidal height `h0`. The arrays `xl`, `yl`, and `zl` may have any shape, as long as they are all the same size. They are measured in the same length units as the semimajor axis. `phi0` and `lambda0` are scalars measured in radians; `h0` is a scalar with the same length units as the semimajor axis; and `ellipsoid` is a `referenceEllipsoid` (`oblateSpheroid`) object, a `referenceSphere` object, or a vector of the form `[semimajor axis, eccentricity]`. The coordinates `x`, `y`, and `z` also have the same units as the semimajor axis.

Definitions

Local Vertical System

In the local vertical Cartesian system defined by `phi0`, `lambda0`, `h0`, and `ellipsoid`, the `xl` axis is parallel to the plane tangent to the ellipsoid at `(phi0,lambda0)` and points due east. The `yl` axis is parallel to the same plane and points due north. The `zl` axis is normal to the ellipsoid at `(phi0,lambda0)` and points outward into space. The local vertical system is sometimes referred to as East-North-Up or ENU.

Geocentric System

The geocentric Cartesian coordinate system, also known as Earth-Centered, Earth-Fixed (ECEF), is fixed with respect to the Earth, with its origin at the center of the spheroid and its positive X-, Y-, and Z axes intersecting the surface at the following points:

| | Latitude | Longitude | Notes |
|--------|-----------------|------------------|-------------------------------|
| X-axis | 0 | 0 | Equator at the Prime Meridian |
| Y-axis | 0 | 90 | Equator at 90-degrees East |
| Z-axis | 90 | 0 | North Pole |

See Also

[ecf2enu](#)

Introduced before R2006a

majaxis

Semimajor axis of ellipse

Note Support for nonscalar input, including the syntax `a = majaxis(vec)`, will be removed in a future release.

Syntax

```
a = majaxis(semimajor,e)
a = majaxis(vec)
```

Description

`a = majaxis(semimajor,e)` computes the semimajor axis of an ellipse (or ellipsoid of revolution) given the semimajor axis and eccentricity. The input data can be scalar or matrices of equal dimensions.

`a = majaxis(vec)` assumes a 2 element vector (`vec`) is supplied, where `vec = [semimajor, e]`.

See Also

`axes2ecc` | `flat2ecc` | `minaxis` | `n2ecc`

Introduced before R2006a

makeattribspec

Attribute specification from geographic data structure

Syntax

```
attribspec = makeattribspec(S)
```

Description

`attribspec = makeattribspec(S)` creates an attribute specification from `S` suitable for use with `kmlwrite`. `S` can be any of the following:

- `geopoint` vector
- `geoshape` vector, with 'point' Geometry and no dynamic vertex properties
- `geostruct` with 'Lat' and 'Lon' coordinate fields

The return value, `attribspec`, is a scalar MATLAB structure with two levels. The top level consists of a field for each attribute in `S`. Each of these fields contains a scalar structure with a fixed pair of fields:

| | |
|-----------------------|--|
| AttributeLabel | A character vector that corresponds to the name of the attribute field in <code>S</code> . With <code>kmlwrite</code> , the character vector is used to label the attribute in the first column of the HTML table. The character vector may be modified prior to calling <code>kmlwrite</code> . You might modify an attribute label, for example, because you want to use spaces in your HTML table, but the attribute field names in <code>S</code> must be valid MATLAB variable names and cannot have spaces themselves. |
| Format | The <code>sprintf</code> format character specification that converts the attribute value to a character vector. |

Examples

- 1 Import a shapefile representing *tsunami* (tidal wave) events reported between 1950 and 2006 and tagged geographically by source location, and construct a default attribute specification (which includes all the shapefile attributes):

```
s = shaperead('tsunamis', 'UseGeoCoords', true);
attribspec = makeattribspec(s)
attribspec =
```

```
    Year: [1x1 struct]
   Month: [1x1 struct]
    Day: [1x1 struct]
   Hour: [1x1 struct]
  Minute: [1x1 struct]
  Second: [1x1 struct]
 Val_Code: [1x1 struct]
 Validity: [1x1 struct]
Cause_Code: [1x1 struct]
   Cause: [1x1 struct]
  Eq_Mag: [1x1 struct]
  Country: [1x1 struct]
  Location: [1x1 struct]
Max_Height: [1x1 struct]
  Iida_Mag: [1x1 struct]
  Intensity: [1x1 struct]
 Num_Deaths: [1x1 struct]
Desc_Deaths: [1x1 struct]
```

- 2 Modify the attribute specification to

- Display just the attributes `Max_Height`, `Cause`, `Year`, `Location`, and `Country`
- Rename the `Max_Height` field to `Maximum Height`
- Display each attribute's label in bold type
- Set to zero the number of decimal places used to display `Year`
- Add “Meters” to the `Height` format, given independent knowledge of these units

```
desiredAttributes = ...
    {'Max_Height', 'Cause', 'Year', 'Location', 'Country'};
allAttributes = fieldnames(attribspec);
attributes = setdiff(allAttributes, desiredAttributes);
attribspec = rmfield(attribspec, attributes);
attribspec.Max_Height.AttributeLabel = '<b>Maximum Height</b>';
```

```
attribspec.Max_Height.Format = '%.1f Meters';
attribspec.Cause.AttributeLabel = '<b>Cause</b>';
attribspec.Year.AttributeLabel = '<b>Year</b>';
attribspec.Year.Format = '%.0f';
attribspec.Location.AttributeLabel = '<b>Location</b>';
attribspec.Country.AttributeLabel = '<b>Country</b>';
```

- 3 Use the attribute specification to export the selected attributes and source locations to a KML file as a Description:

```
filename = 'tsunami.kml';
kmlwrite(filename, s, 'Description', attribspec, ...
    'Name', {s.Location})
```

See also

kmlwrite, makedbfspec, shapewrite

Tips

- The easiest way to construct an attribute specification is to create one, using `makeattribspec`, and then modify the output, removing attributes or changing the `Format` field for one or more attributes.
- You can use an attribute specification with `kmlwrite` as the value of the `Description` parameter. `kmlwrite` constructs an HTML table that consists of a label for the attribute in the first column and the value of the attribute in the second column. You can modify the attribute specification to control which attribute fields are written to the HTML table and their format.

makedbfspec

DBF specification from geographic data structure

Syntax

```
dbfspec = makedbfspec(S)
```

Description

`dbfspec = makedbfspec(S)` analyzes a geographic data structure, `S`, and constructs a DBF specification suitable for use with `shapewrite`. You can modify `dbfspec`, then pass it to `shapewrite` to exert control over which `geostruct` attribute fields are written to the DBF component of the shapefile, the field-widths, and the precision used for numerical values.

`dbfspec` is a scalar MATLAB structure with two levels. The top level consists of a field for each attribute in `S`. Each of these fields, in turn, contains a scalar structure with a fixed set of four fields:

| dbfspec field | Contents |
|----------------------|--|
| FieldName | The field name to be used within the DBF file. This name will be identical to the name of the corresponding attribute, but may be modified prior to calling <code>shapewrite</code> . This modification might be necessary, for example, because you want to use spaces in your DBF field names but know that you cannot use spaces for MATLAB variable names. |
| FieldType | The field type to be used in the file, either 'N' (numeric) or 'C' (character). |
| FieldLength | The number of bytes that each instance of the field will occupy in the file. |

| dbfspec field | Contents |
|-------------------|---|
| FieldDecimalCount | The number of digits to the right of the decimal place that are kept in a numeric field. Zero for integer-valued fields and character fields. The default value for noninteger numeric fields is 6. |

Examples

Import a shapefile representing a small network of road segments, and construct a DBF specification.

```
s = shaperead('concord_roads')

s =
609x1 struct array with fields:
    Geometry
    BoundingBox
    X
    Y
    STREETNAME
    RT_NUMBER
    CLASS
    ADMIN_TYPE
    LENGTH
```

```
dbfspec = makedbfspec(s)
```

```
dbfspec =
    STREETNAME: [1x1 struct]
    RT_NUMBER: [1x1 struct]
    CLASS: [1x1 struct]
    ADMIN_TYPE: [1x1 struct]
    LENGTH: [1x1 struct]
```

Modify the DBF spec to (a) eliminate the 'ADMIN_TYPE' attribute, (b) rename the 'STREETNAME' field to 'Street Name', and (c) reduce the number of decimal places used to store road lengths.

```
dbfspec = rmfield(dbfspec, 'ADMIN_TYPE')
```

```
dbfspec =
```

```
STREETNAME: [1x1 struct]
RT_NUMBER: [1x1 struct]
  CLASS: [1x1 struct]
  LENGTH: [1x1 struct]
```

```
dbfspec.STREETNAME.FieldName = 'Street Name';
dbfspec.LENGTH.FieldDecimalCount = 1;
```

Export the road network back to a modified shapefile. (Actually, only the DBF component will be different.)

```
shapewrite(s, 'concord_roads_modified', 'DbfSpec', dbfspec)
```

Verify the changes you made. Notice the appearance of 'Street Name' in the field names reported by `shapeinfo`, the absence of the 'ADMIN_TYPE' field, and the reduction in the precision of the road lengths.

```
info = shapeinfo('concord_roads_modified')
info =
  Filename: [3x28 char]
  ShapeType: 'PolyLine'
  BoundingBox: [2x2 double]
  NumFeatures: 609
  Attributes: [4x1 struct]

{info.Attributes.Name}

ans =
  'Street Name'    'RT_NUMBER'    'CLASS'    'LENGTH'

r = shaperead('concord_roads_modified')

r =
609x1 struct array with fields:
  Geometry
  BoundingBox
  X
  Y
  StreetName
  RT_NUMBER
  CLASS
  LENGTH

s(33).LENGTH
```

```
ans =  
  3.4928174000000000e+002
```

```
r(33).LENGTH
```

```
ans =  
  3.4930000000000000e+002
```

See also

shapeinfo, shapewrite

Introduced before R2006a

makemapped

Convert ordinary graphics object to mapped object

Note makemapped will be removed in a future release.

Syntax

makemapped(h)

Description


makemapped(h) modifies the graphic object(s) associated with h such that upon subsequent modification of map axes properties, they are automatically reprojected appropriately. The object's coordinates are not changed by makemapped, but will change should you modify the map projection. h can be a handle, vector of handles, or any name recognized by handlem. The objects are then considered to be geographic data. You should first trim objects extending outside the map frame to the map frame using trimcart.

Examples

```
axesm('miller','geoid',[25 0])
framem
plot(humps,'b+-')

h = plot(humps,'r+-');
trimcart(h)
makemapped(h)

setm(gca,'MapProjection','sinusoid')
```

Tips

Objects should first be trimmed to the map frame using `trimcart`. This avoids problems in taking inverse map projections with out-of-range data.

See Also

makerefmat

Construct affine spatial-referencing matrix

Syntax

```
R = makerefmat(x11, y11, dx, dy)
R = makerefmat(lon11, lat11, dlon, dlat)
R = makerefmat(param1, val1, param2, val2, ...)
```

Description

`R = makerefmat(x11, y11, dx, dy)`, with scalars `dx` and `dy`, constructs a referencing matrix that aligns image or data grid rows to map `x` and columns to map `y`. Scalars `x11` and `y11` specify the map location of the center of the first (1,1) pixel in the image or the first element of the data grid, so that

```
[x11 y11] = pix2map(R,1,1)
```

`dx` is the difference in `x` (or longitude) between pixels in successive columns, and `dy` is the difference in `y` (or latitude) between pixels in successive rows. More abstractly, `R` is defined such that

```
[x11 + (col-1) * dx, y11 + (row-1) * dy] = pix2map(R, row, col)
```

Pixels cover squares on the map when `abs(dx) = abs(dy)`. To achieve the most typical kind of alignment, where `x` increases from column to column and `y` decreases from row to row, make `dx` positive and `dy` negative. In order to specify such an alignment along with square pixels, make `dx` positive and make `dy` equal to `-dx`:

```
R = makerefmat(x11, y11, dx, -dx)
```

`R = makerefmat(x11, y11, dx, dy)`, with two-element vectors `dx` and `dy`, constructs the most general possible kind of referencing matrix, for which

```
[x11 + ([row col]-1) * dx(:), y11 + ([row col]-1) * dy(:)] ...
= pix2map(R, row, col)
```

In this general case, each pixel can become a parallelogram on the map, with neither edge necessarily aligned to map x or y . The vector $[dx(1) \ dy(1)]$ is the difference in map location between a pixel in one row and its neighbor in the preceding row. Likewise, $[dx(2) \ dy(2)]$ is the difference in map location between a pixel in one column and its neighbor in the preceding column.

To specify pixels that are rectangular or square (but possibly rotated), choose dx and dy such that $\text{prod}(dx) + \text{prod}(dy) = 0$. To specify square (but possibly rotated) pixels, choose dx and dy such that the 2-by-2 matrix $[dx(\ :) \ dy(\ :)]$ is a scalar multiple of an orthogonal matrix (that is, its two eigenvalues are real, nonzero, and equal in absolute value). This amounts to either rotation, a mirror image, or a combination of both. Note that for scalars dx and dy ,

```
R = makereformat(x11, y11, [0 dx], [dy 0])
```

is equivalent to

```
R = makereformat(x11, y11, dx, dy)
```

$R = \text{makereformat}(\text{lon11}, \text{lat11}, \text{dlon}, \text{dlat})$, with longitude preceding latitude, constructs a referencing matrix for use with geographic coordinates. In this case,

```
[lat11,lon11] = pix2latlon(R,1,1),
[lat11+(row-1)*dlat,lon11+(col-1)*dlon] = pix2latlon(R,row,col)
```

for scalar $dlat$ and $dlon$, and

```
[lat11+[row col]-1)*dlat,lon11+([row col]-1)*dlon] = ...
pix2latlon(R, row,col)
```

for vector $dlat$ and $dlon$. Images or data grids aligned with latitude and longitude might already have referencing vectors. In this case you can use function `refvec2mat` to convert to a referencing matrix.

$R = \text{makereformat}(\text{param1}, \text{val1}, \text{param2}, \text{val2}, \dots)$ uses parameter name-value pairs to construct a referencing matrix for an image or raster grid that is referenced to and aligned with a geographic coordinate system. There can be no rotation or skew: each column must fall along a meridian, and each row must fall along a parallel. Each parameter name must be specified exactly as shown, including case.

| Parameter Name | Data Type | Value |
|------------------|---|--|
| RasterSize | Two-element size vector [M N] | <p>The number of rows (M) and columns (N) of the raster or image to be used with the referencing matrix.</p> <p>With 'RasterSize', you may also provide a size vector having more than two elements. This enables usage such as:</p> <pre>R = makerefmat('RasterSize', ... size(RGB), ...)</pre> <p>where RGB is M-by-N-by-3. However, in cases like this, only the first two elements of the size vector will actually be used. The higher (non-spatial) dimensions will be ignored. The default value is [1 1].</p> |
| LatitudeLimits | Two-element row vector of the form: [southern_limit, northern_limit], in units of degrees. | The limits in latitude of the geographic quadrangle bounding the georeferenced raster. The default value is [0 1]. |
| LongitudeLimits | Two-element row vector of the form: [western_limit, eastern_limit], in units of degrees. | The limits in longitude of the geographic quadrangle bounding the georeferenced raster. The elements of the 'LongitudeLimits' vector must be ascending in value. In other words, the limits must be unwrapped. The default value is [0 1]. |
| ColumnsStartFrom | String scalar or character vector | Indicates the column direction of the raster (south-to-north vs. north-to-south) in terms of the edge from which row indexing starts. Values are 'south' or 'north' and they can be shortened, and are case-insensitive. In a typical terrain grid, row indexing starts at southern edge. In images, row indexing starts at northern edge. The default value is 'south'. |

| Parameter Name | Data Type | Value |
|----------------|-----------------------------------|--|
| RowsStartFrom | String scalar or character vector | Indicates the row direction of the raster (west-to-east vs. east-to-west) in terms of the edge from which column indexing starts. Values are: 'west' or 'east' and they can be shortened, and are case-insensitive. Rows almost always run from west to east. The default value is 'west'. |

Examples

Create a referencing matrix for an image with square, four-meter pixels and with its upper left corner (in a map coordinate system) at $x = 207000$ meters, $y = 913000$ meters. The image follows the typical orientation: x increasing from column to column and y decreasing from row to row.

```
x11 = 207002; % Two meters east of the upper left corner
y11 = 912998; % Two meters south of the upper left corner
dx = 4;
dy = -4;
R = makereformat(x11, y11, dx, dy)
```

Create a referencing matrix for a global geoid grid.

```
% Add array 'geoid' to the workspace:
load geoid

%'geoid' contains a model of the Earth's geoid sampled in
% one-degree-by-one-degree cells. Each column of 'geoid'
% contains geoid heights in meters for 180 cells starting
% at latitude -90 degrees and extending to +90 degrees, for
% a given longitude. Each row contains geoid heights for 360
% cells starting at longitude 0 and extending 360 degrees.
geoidR = makereformat('RasterSize', size(geoid), ...
    'Latlim', [-90 90], 'Lonlim', [0 360])

% At its most extreme, the geoid reaches a minimum of slightly
% less than -100 meters. This minimum occurs in the Indian Ocean
% at approximately 4.5 degrees latitude, 78.5 degrees longitude.
% Check the geoid height at its most extreme by using latlon2pix
% with the referencing matrix.
```

```
[row, col] = latlon2pix(geoidR, 4.5, 78.5)
geoid(round(row),round(col))
```

Definitions

Spatial Referencing Matrix

A spatial referencing matrix R ties the row and column subscripts of an image or regular data grid to 2-D map coordinates or to geographic coordinates (longitude and geodetic latitude). R is a 3-by-2 affine transformation matrix. R either transforms pixel subscripts (row, column) to/from map coordinates (x,y) according to

$$[x \ y] = [\text{row} \ \text{col} \ 1] * R$$

or transforms pixel subscripts to/from geographic coordinates according to

$$[\text{lon} \ \text{lat}] = [\text{row} \ \text{col} \ 1] * R$$

To construct a referencing matrix for use with geographic coordinates, use longitude in place of X and latitude in place of Y, as shown in the `R = makerefmat(X11, Y11, dx, dy)` syntax. This is one of the few places where longitude precedes latitude in a function call.

See Also

[latlon2pix](#) | [map2pix](#) | [pix2latlon](#) | [pix2map](#) | [refvec2mat](#) | [worldfileread](#) | [worldfilewrite](#)

Topics

“Creating a Half-Resolution Georeferenced Image”

makesymbolspec

Construct vector layer symbolization specification

Syntax

```
symbolspec = makesymbolspec(geometry, rule1, rule2, ... ruleN)
```

Description

`symbolspec = makesymbolspec(geometry, rule1, rule2, ... ruleN)` constructs a symbol specification structure (`symbolspec`) for symbolizing a (vector) shape layer in the Map Viewer or when using `mapshow`. `geometry` is one of 'Point', 'Line', 'PolyLine', 'Polygon', or 'Patch'. Rules, defined in detail below, specify the graphics properties for each feature of the layer. A rule can be a default rule that is applied to all features in the layer or it may limit the symbolization to only those features that have a particular value for a specified attribute. Features that do not match any rules are displayed using the default graphics properties.

To create a rule that applies to all features, a default rule, use the following syntax:

```
{'Default', Property1, Value1, Property2, Value2, ...  
    PropertyN, ValueN}
```

To create a rule that applies only to features that have a particular value or range of values for a specified attribute, use the following syntax:

```
{AttributeName, AttributeValue,  
    Property1, Value1, Property2, Value2, ..., PropertyN, ValueN}
```

`AttributeValue` and `ValueN` can each be a two-element vector, `[low high]`, specifying a range. If `AttributeValue` is a range, `ValueN` might or might not be a range.

The following is a list of allowable values for `PropertyN`.

- Points or Multipoints: 'Marker', 'Color', 'MarkerEdgeColor', 'MarkerFaceColor', 'MarkerSize', and 'Visible'


- Lines or PolyLines: 'Color', 'LineStyle', 'LineWidth', and 'Visible'
- Polygons: 'FaceColor', 'FaceAlpha', 'LineStyle', 'LineWidth', 'EdgeColor', 'EdgeAlpha', and 'Visible'

Examples

The following examples import a shapefile containing road data and symbolize it in several ways using symbol specifications.

Example 1 — Default Color

```
roads = shaperead('concord_roads.shp');  
blueRoads = makesymbolspec('Line',{'Default','Color',[0 0 1]});  
mapshow(roads,'SymbolSpec',blueRoads);
```



Example 2 — Discrete Attribute Based


```
roads = shaperead('concord_roads.shp');  
roadColors = ...
```



```

makesymbolspec('Line',{ 'CLASS',2,'Color','r'},...
               { 'CLASS',3,'Color','g'},...
               { 'CLASS',6,'Color','b'},...
               { 'Default','Color','k'});
mapshow(roads,'SymbolSpec',roadColors);

```




Example 3 — Using a Range of Attribute Values

```


roads = shaperead('concord_roads.shp');
lineStyle = makesymbolspec('Line',...
    { 'CLASS',[1 3], 'LineStyle',':'},...
    { 'CLASS',[4 6], 'LineStyle','-.'});
mapshow(roads,'SymbolSpec',lineStyle);

```



Example 4 — Using a Range of Attribute Values and a Range of Property Values

```
roads = shaperead('concord_roads.shp');  
colorRange = makesymbolspec('Line',...  
                             {'CLASS',[1 6],'Color',summer(10)});  
mapshow(roads,'SymbolSpec',colorRange);
```



See Also

[geoshow](#) | [mapshow](#) | [mapview](#)

Introduced before R2006a

map2pix

Convert map coordinates to pixel coordinates

Syntax

```
[row,col] = map2pix(R,x,y)
p = map2pix(R,x,y)
[...] = map2pix(R,s)
```

Description

`[row,col] = map2pix(R,x,y)` calculates pixel coordinates `row`, `col` from map coordinates `x`, `y`. `R` is either a 3-by-2 referencing matrix defining a 2-dimensional affine transformation from intrinsic pixel coordinates to map coordinates, or a map raster reference object. `x` and `y` are vectors or arrays of matching size. The outputs `row` and `col` have the same size as `x` and `y`.

`p = map2pix(R,x,y)` combines `row` and `col` into a single array `p`. If `x` and `y` are column vectors of length `n`, then `p` is an `n`-by-2 matrix and each `p(k,:)` specifies the pixel coordinates of a single point. Otherwise, `p` has size `[size(row) 2]`, and `p(k1,k2,...,kn,:)` contains the pixel coordinates of a single point.

`[...] = map2pix(R,s)` combines `x` and `y` into a single array `s`. If `x` and `y` are column vectors of length `n`, the `s` should be an `n`-by-2 matrix such that each row (`s(k,:)`) specifies the map coordinates of a single point. Otherwise, `s` should have size `[size(X) 2]`, and `s(k1,k2,...,kn,:)` should contain the map coordinates of a single point.

Examples

```
% Find the pixel coordinates for the spatial coordinates
% (207050, 912900)
R = worldfileread('concord_ortho_w.tifw');
[r,c] = map2pix(R, 207050, 912900);
```

See Also

latlon2pix | makerefmat | pix2map | worldfileread

Introduced before R2006a

mapbbox

Compute bounding box of georeferenced image or data grid

Syntax

```
bbox = mapbbox(R,height,width)
bbox = mapbbox(R, sizea)
BBOX = mapbbox(info)
```

Description

`bbox = mapbbox(R,height,width)` computes the 2-by-2 bounding box of a georeferenced image or regular gridded data set. `R` is either a 3-by-2 referencing matrix defining a 2-dimensional affine transformation from intrinsic pixel coordinates to map coordinates, or a `MapCellsReference` object. (If you are using a raster reference object, you can calculate the bounding box from the object limit properties of the object rather than using this function.) `height` and `width` are the image dimensions. `bbox` bounds the outer edges of the image in map coordinates:

```
[minX minY
maxX maxY]
```

`bbox = mapbbox(R, sizea)` accepts `sizea = [height, width, ...]` instead of `height` and `width`.

`BBOX = mapbbox(info)` accepts a scalar struct array with the fields

| | |
|-------------|---------------------------|
| 'RefMatrix' | 3-by-2 referencing matrix |
| 'Height' | Scalar number |
| 'Width' | Scalar number |

See Also

[geotiffinfo](#) | [makerefmat](#) | [mapoutline](#) | [pix2map](#) | [pixcenters](#)

Introduced before R2006a

MapCellsReference

Reference raster cells to map coordinates

Description

A map cells reference object encapsulates the relationship between a planar map coordinate system and a system of intrinsic coordinates anchored to the columns and rows of a 2-D spatially referenced raster grid or image.

Typically, the raster is sampled regularly in the planar world x and world y coordinates of the map system, such that the intrinsic x and world x axes align and the intrinsic y and world y axes align. When this is true, the relationship between the two systems is rectilinear. More generally, and much more rarely, their relationship is affine. The affine relationship allows for a possible rotation (and skew). In either case, rectilinear or affine, the sample spacing from row to row need not equal the sample spacing from column to column. The cells or pixels need not be square. In the most general case, they could conceivably be parallelograms, but in practice they are always rectangular. For more information about coordinate systems, see “Intrinsic Coordinate System” on page 1-859.

Creation

You can use any of the following functions to create a `MapCellsReference` object to reference a regular raster of cells to planar (map) coordinates.

- `maprefcells` — Create a map raster reference object.
- `maprasterref` — Convert a world file to a map raster reference object.
- `refmatToMapRasterReference` — Convert a referencing matrix to a map raster reference object.

For example, this syntax constructs a `MapCellsReference` object with default property settings:

```
R = maprefcells()
```

```
R =
```


MapCellsReference with properties:

```

XWorldLimits: [0.5 2.5]
YWorldLimits: [0.5 2.5]
RasterSize: [2 2]
RasterInterpretation: 'cells'
ColumnsStartFrom: 'south'
RowsStartFrom: 'west'
CellExtentInWorldX: 1
CellExtentInWorldY: 1
RasterExtentInWorldX: 2
RasterExtentInWorldY: 2
XIntrinsicLimits: [0.5 2.5]
YIntrinsicLimits: [0.5 2.5]
TransformationType: 'rectilinear'
CoordinateSystemType: 'planar'

```

Properties

XWorldLimits — Limits of raster in world x-coordinates

[0.5 2.5] (default) | two-element row vector

Limits of raster in world x-coordinates, specified as a two-element row vector of the form [xMin xMax].

Example: [207000 209000]

Data Types: double

YWorldLimits — Limits of raster in world y-coordinates

[0.5 2.5] (default) | two-element row vector

Limits of raster in world y-coordinates, specified as a two-element row vector of the form [yMin yMax].

Example: [911000 913000]

Data Types: double

RasterSize — Number of rows and columns of the raster or image associated with the referencing object

[2 2] (default) | two-element vector of positive integers

Number of rows and columns of the raster or image associated with the referencing object, specified as a two-element vector, $[m\ n]$, where m represents the number of rows and n the number of columns.

For convenience, you can assign a size vector having more than two elements. This enables assignments like `R.RasterSize = size(RGB)`, where `RGB` is m -by- n -by-3. In cases like this, the object stores only the first two elements of the size vector and ignores the higher (nonspatial) dimensions.

Example: `[200 300]`

Data Types: `double`

RasterInterpretation — Geometric nature of the raster

`'cells'` (default)

This property is read-only.

Geometric nature of the raster, specified as `'cells'`. The value `'cells'` indicates that the raster comprises a grid of quadrangular cells, and is bounded on all sides by cell edges. For an m -by- n raster, points with an intrinsic x -coordinate of 1 or n or an intrinsic x -coordinate of 1 or m fall within the raster, not on its edges.

Data Types: `char`

ColumnsStartFrom — Edge from which column indexing starts

`'south'` (default) | `'north'`

Edge from which column indexing starts, specified as `'south'` or `'north'`.

Example: `'south'`

Data Types: `char`

RowsStartFrom — Edge from which row indexing starts

`'west'` (default) | `'east'`

Edge from which row indexing starts, specified as `'west'` or `'east'`.

Example: `'east'`

Data Types: `char`

CellExtentInWorldX — Extent in world x -coordinates of individual cells

1 (default) | positive numeric scalar

Extent in world x -coordinates of individual cells, specified as a positive numeric scalar. Distance between the eastern and western limits of a single raster cell. The value is the same for all cells in the raster.

Example: 2.5

Data Types: double

CellExtentInWorldY — Extent in world y -coordinates of individual cells

1 (default) | positive numeric scalar

Extent in world y -coordinates of individual cells, specified as a positive numeric scalar. Distance between the northern and southern limits of a single raster cell. The value is the same for all cells in the raster.

Example: 2.5

Data Types: double

RasterExtentInWorldX — Extent of the full raster or image as measured in the world system in a direction parallel to its rows

2 (default) | positive numeric scalar

This property is read-only.

Extent of the full raster or image as measured in the world system in a direction parallel to its rows, specified as a positive numeric scalar. In the case of a rectilinear geometry, which is most typical, this is the horizontal direction (east-west).

Data Types: double

RasterExtentInWorldY — Extent of the full raster or image as measured in the world system in a direction parallel to its columns

2 (default) | positive numeric scalar

This property is read-only.

Extent of the full raster or image as measured in the world system in a direction parallel to its columns, specified as a positive numeric scalar. In the case of a rectilinear geometry, which is most typical, this is the vertical direction (north-south).

Data Types: double

XIntrinsicLimits — Raster limits in intrinsic x -coordinates

[0.5 2.5] (default) | two-element row vector of positive integers

This property is read-only.

Raster limits in intrinsic x-coordinates, specified as a two-element row vector of positive integers, [xMin xMax]. For an *m*-by-*n* raster, XIntrinsicLimits equals [0.5, m + 0.5], because the RasterInterpretation is 'cells'.

Data Types: double

YIntrinsicLimits — Raster limits in intrinsic y-coordinates

[0.5 2.5] (default) | two-element row vector of positive integers

This property is read-only.

Raster limits in intrinsic y-coordinates, specified as a two-element row vector of positive integers, [yMin yMax]. For an *m*-by-*n* raster, YIntrinsicLimits equals [0.5, m + 0.5], because the RasterInterpretation is 'cells'.

Data Types: double

TransformationType — Type of geometric relationship between intrinsic and world systems

'rectilinear' (default) | 'affine'

This property is read-only.

Type of geometric relationship between the intrinsic coordinate system and the world coordinate system, specified as either 'rectilinear' or 'affine'. Its value is 'rectilinear' when world x depends only on intrinsic x and vice versa, and world y depends only on intrinsic y and vice versa. When the value is 'rectilinear', the image displays without rotation in the world system, although it might be flipped. Otherwise, the value is 'affine'.

Data Types: char

CoordinateSystemType — Type of coordinate system to which the image or raster is referenced

'planar' (default)

This property is read-only.

Type of coordinate system to which the image or raster is referenced, specified as 'planar'.

Data Types: char

Object Functions

| | |
|-------------------------------|--|
| <code>contains</code> | Determine if geographic or map raster contains points |
| <code>firstCornerX</code> | Return world x-coordinate of map raster index (1,1) |
| <code>firstCornerY</code> | Return world y-coordinate of map raster index (1,1) |
| <code>intrinsicToWorld</code> | Transform intrinsic to planar world coordinates |
| <code>sizesMatch</code> | Determine if geographic or map raster object and image or raster are size-compatible |
| <code>worldFileMatrix</code> | Return world file parameters for transformation |
| <code>worldToDiscrete</code> | Transform planar world to discrete coordinates |
| <code>worldToIntrinsic</code> | Transform planar world to intrinsic coordinates |

Definitions

Intrinsic Coordinate System

A 2-D Cartesian system with its x -axis running parallel to the rows of a raster or image and its y -axis running parallel to the columns. x increases by 1 from column to column, and y increases by 1 from row to row.

The Mapping Toolbox and Image Processing Toolbox use the convention for the location of the origin relative to the raster cells or sampling points such that, at a sample location or at the center of a cell, x has an integer value equal to the column index. Likewise, at a sample location or at the center of a cell, y has an integer value equal to the row index. For details, see Image Coordinate Systems (Image Processing Toolbox).

See Also

Functions

`maprasterref` | `maprefpostings`

Objects

`GeographicCellsReference` | `GeographicPostingsReference` | `MapPostingsReference`

Introduced in R2013b

mapinterp

Map raster interpolation

Syntax

```
Vq = mapinterp(V,R,xq,yq)
Vq = mapinterp( ____,method)
```

Description

`Vq = mapinterp(V,R,xq,yq)` interpolates the spatially referenced raster `V`, using bilinear interpolation. The function returns a value in `Vq` for each of the query points in arrays `xq` and `yq`. `R` is a map raster reference object that specifies the location and extent of data in `V`.

`Vq = mapinterp(____,method)` specifies alternate interpolation methods.

Examples


Interpolate Spatially Referenced Raster Grid at Defined Coordinates

Load a spatially referenced raster grid and a map raster reference object. This example uses projected elevation data for Mt. Washington.

```
[Z, R] = arcgridread('MtWashington-ft.grd','planar');
```

Display the data using `mapshow`.

```
figure
mapshow(Z,R,'DisplayType','texturemap')
colorbar
```



Define the points you want to interpolate.

```
x = [312829 317447 316083 311150];
y = [4913618 4912253 4904329 4904172];
```

Interpolate the values at the defined points.

```
Vinterpolated = mapinterp(Z,R,x,y)
```

```
Vinterpolated = 1×4
103 ×
```

```
1.5240 3.6780 6.2363 2.3646
```

Input Arguments

V — Spatially referenced raster grid

numeric or logical array

Spatially referenced raster grid, specified as numeric or logical array.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64` | `logical`

R — Map raster

`MapCellsReference` or `MapPostingsReference` object

Map raster, specified as a `MapCellsReference` or `MapPostingsReference` object.

To convert a referencing matrix to a map raster reference object, use `refmatToMapRasterReference`.

xq — Query point coordinates in x dimension

numeric array

Query point coordinates in x dimension, specified as a numeric array.

Data Types: `single` | `double`

yq — Query point coordinates in y dimension

numeric array

Query point coordinates in y dimension, specified as a numeric array.

Data Types: `single` | `double`

method — Interpolation methods

`'linear'` (default) | `'nearest'` | `'cubic'` | `'spline'`

Interpolation methods, specified as one of these values:

| Method | Description |
|------------------------|--------------------------------|
| <code>'nearest'</code> | Nearest neighbor interpolation |
| <code>'linear'</code> | Bilinear interpolation |
| <code>'cubic'</code> | Bicubic interpolation |

| Method | Description |
|----------|----------------------|
| 'spline' | Spline interpolation |

Data Types: char | string

Output Arguments

Vq — Interpolated values

numeric array

Interpolated values, returned as a numeric array.

See Also

geointerp | griddedInterpolant | interp2

Introduced in R2017a

maplist

Available Mapping Toolbox map projections

Syntax

```
list = maplist  
[list,defproj] = maplist
```

Description

`list = maplist` returns a structure that lists all the available Mapping Toolbox map projections. The list structure is `list.Name`, `list.IdString`, `list.Classification`, `list.ClassCode`. This list structure is used by the functions `maps` and `axesmui` when processing map projection identifiers during operation of the toolbox functions.

`[list,defproj] = maplist` also returns the default projection's `IdString`.

`list.Name` defines the full name of the projection. This entry is used in the command-line table display and in the Projection Control Box.

`list.IdString` provides the name of the MATLAB function that computes the projection.

`list.Classification` defines the projection classification that is used in the command-line table display.

`list.ClassCode` defines the character vector that is used to label the classes of projections in the Projection Control Box. The eight class codes are

- `Azim` — Azimuthal
- `Coni` — Conic
- `Cyln` — Cylindrical
- `Mazi` — Modified azimuthal
- `Pazi` — Pseudoazimuthal

- Pcon — Pseudoconic
- Pcy — Pseudocylindrical
- Poly — Polyconic

See Also

axesmui | maps

mapoutline

Compute outline of georeferenced image or data grid

Syntax

```
[x,y] = mapoutline(R,height,width)
[x,y] = mapoutline(R, sizea)
[x,y] = mapoutline(info)
[x,y] = mapoutline(...,'close')
[lon,lat] = mapoutline(R,...)
outline = mapoutline(...)
```

Description

`[x,y] = mapoutline(R,height,width)` computes the outline of a georeferenced image or regular gridded data set in map coordinates. `R` is either a 3-by-2 referencing matrix defining a 2-dimensional affine transformation from intrinsic pixel coordinates to map coordinates, or a `MapCellsReference` or `MapPostingsReference` object. `height` and `width` are the image dimensions. `x` and `y` are 4-by-1 column vectors containing the map coordinates of the outer corners of the corner pixels, in the following order:

`(1,1), (height,1), (height, width), (1, width)`.

`[x,y] = mapoutline(R, sizea)` accepts `sizea = [height, width, ...]` instead of `height` and `width`.

`[x,y] = mapoutline(info)` accepts a scalar struct array with the fields

| | |
|-------------|---------------------------|
| 'RefMatrix' | 3-by-2 referencing matrix |
| 'Height' | Scalar number |
| 'Width' | Scalar number |

`[x,y] = mapoutline(...,'close')` returns `x` and `y` as 5-by-1 vectors, appending the coordinates of the first of the four corners to the end.

`[lon,lat] = mapoutline(R,...)`, where R georeferences pixels to longitude and latitude rather than map coordinates, returns the outline in geographic coordinates. Longitude must precede latitude in the output argument list.

`outline = mapoutline(...)` returns the corner coordinates in a 4-by-2 or 5-by-2 array.


Examples

Draw a red outline delineating the Boston GeoTIFF image, which is referenced to the Massachusetts Mainland State Plane coordinate system with units of survey feet.

```
figure
info = geotiffinfo('boston.tif');
[x,y] = mapoutline(info, 'close');
hold on
plot(x,y,'r')
xlabel('MA Mainland State Plane easting, survey feet')
ylabel('MA Mainland State Plane northing, survey feet')
```

Draw a black outline delineating a TIFF image of Concord, Massachusetts, while lies roughly 25 km north west of Boston. Convert world file units to survey feet from meters to be consistent with the Boston image.

```
info = imfinfo('concord_ortho_w.tif');
R = worldfileread('concord_ortho_w.tfw');
R = R * unitsratio('sf','meter');
[x,y] = mapoutline(R, info.Height, info.Width, 'close');
plot(x,y,'k')
```



See Also

Functions

[makerefmat](#) | [mapbbox](#) | [pix2map](#) | [pixcenters](#)

Objects

[MapCellsReference](#) | [MapPostingsReference](#)

Introduced before R2006a

mappoint

Planar point vector

Description

A mappoint vector is a container object that holds planar point coordinates and attributes. The points are coupled, such that the size of the x- and y-coordinate arrays are always equal and match the size of any dynamically added attribute arrays. Each entry of a coordinate pair and associated attributes, if any, represents a discrete element in the mappoint vector.

Creation

Syntax

```
p = mappoint()  
p = mappoint(x,y)  
p = mappoint(x,y,Name,Value)  
p = mappoint(structArray)  
p = mappoint(x,y,structArray)
```

Description

`p = mappoint()` constructs an empty mappoint vector, `p`, with these default property settings:

```
p =
```

```
0x1 mappoint vector with properties:
```

```
Collection properties:
```

```
    Geometry: 'point'
```

```
    Metadata: [1x1 struct]
```

```
Feature properties:
```

```
X: []  
Y: []
```

`p = mappoint(x,y)` constructs a new `mappoint` vector and assigns the X and Y properties to the numeric array inputs, `x` and `y`.

`p = mappoint(x,y,Name,Value)` constructs a `mappoint` vector, then adds dynamic properties to the `mappoint` vector using `Name`, `Value` argument pairs. You can specify several name-value pair arguments in any order as `Name1,Value1, . . . ,NameN,ValueN`.

`p = mappoint(structArray)` constructs a new `mappoint` vector, assigning the fields of the structure array, `structArray`, as dynamic properties. Field values in `structArray` that are not numeric values, string scalar, string array, character vectors, or cell arrays of numeric values or character vectors are ignored.

`p = mappoint(x,y,structArray)` constructs a new `mappoint` vector, sets the X and Y properties equal to the numeric arrays `x` and `y`, and sets dynamic properties from the field values of `structArray`.

Properties

Each element in a `mappoint` vector is considered a feature. For more about the property types in `mappoint`, see “Collection Properties” on page 1-889 and “Feature Properties” on page 1-889.

Dynamic properties are new features that are added to a `mappoint` vector and that apply to each individual feature in the `mappoint` vector. You can attach dynamic Feature properties to a `mappoint` object during construction with a `Name,Value` pair or after construction using dot (`.`) notation. This is similar to adding dynamic fields to a structure. For an example of adding Feature properties dynamically, see “Construct a Mappoint Vector for Multiple Features and Examine Autosizing” on page 1-875.

Geometry — Type of geometry

```
'point'
```

Type of geometry, specified as `'point'`. For `mappoint`, `Geometry` is always `'point'`.

Data Types: `char` | `string`

Metadata — Information for the entire set of `mappoint` vector elements

```
scalar structure
```


Information for the entire set of mappoint vector elements, specified as a scalar structure. You can add any data type to the structure.

- If `Metadata` is provided as a dynamic property `Name` in the constructor, and the corresponding `Value` is a scalar structure, then `Value` is copied to the `Metadata` property. Otherwise, an error is issued.
- If a `Metadata` field is provided by `structArray`, and both `Metadata` and `structArray` are scalar structures, then the `Metadata` field value is copied to the `Metadata` property value. If `structArray` is a scalar but the `Metadata` field is not a structure, then an error is issued. If `structArray` is not scalar, then the `Metadata` field is ignored.

Data Types: `struct`

X — Planar x-coordinates

numeric row or column vector

Planar x-coordinate, specified as a numeric row or column vector.

Data Types: `double` | `single`

Y — Planar y-coordinates

numeric row or column vector

Planar y-coordinates, specified as a numeric row or column vector.

Data Types: `double` | `single`

Object Functions

| | |
|-------------------------|---|
| <code>append</code> | Append features to geographic or planar vector |
| <code>cat</code> | Concatenate geographic or planar vector |
| <code>disp</code> | Display geographic or planar vector |
| <code>fieldnames</code> | Return dynamic property names of geographic or planar vector |
| <code>isempty</code> | Determine if geographic or planar vector is empty |
| <code>isfield</code> | Determine if dynamic property exists in geographic or planar vector |
| <code>isprop</code> | Determine if property exists in geographic or planar vector |
| <code>length</code> | Return number of elements in geographic or planar vector |
| <code>properties</code> | Return property names of geographic or planar vector |
| <code>rmfield</code> | Remove dynamic property from geographic or planar vector |
| <code>rmprop</code> | Remove property from geographic or planar vector |

| | |
|---------|---|
| size | Return size of geographic or planar vector |
| struct | Convert geographic or planar vector to scalar structure |
| vertcat | Vertically concatenate geographic or planar vectors |

Examples

Construct a Default Mappoint Vector

Dynamically set the X and Y property values, and dynamically add Vertex property Z.

```
p = mappoint();  
p.X = 1:3;  
p.Y = 1:3;  
p.Z = [10 10 10]
```

```
p =
```

```
3x1 mappoint vector with properties:
```

```
Collection properties:  
  Geometry: 'point'  
  Metadata: [1x1 struct]  
Feature properties:  
  X: [1 2 3]  
  Y: [1 2 3]  
  Z: [10 10 10]
```

Construct a Mappoint Vector from X and Y Values

Define x and y coordinates. Use them to create a mappoint.

```
x = [40 50 60];  
y = [10, 11, 12];  
p = mappoint(x, y)
```

```
p =
```

```
3x1 mappoint vector with properties:
```

```
Collection properties:
```

```
Geometry: 'point'  
Metadata: [1x1 struct]  
Feature properties:  
    X: [40 50 60]  
    Y: [10 11 12]
```

Construct a Mappoint Vector from X, Y, and Temperature Values

```
x = 41:43;  
y = 1:3;  
temperature = 61:63;  
p = mappoint(x, y, 'Temperature', temperature)
```

```
p =
```

```
3x1 mappoint vector with properties:
```

```
Collection properties:  
    Geometry: 'point'  
    Metadata: [1x1 struct]  
Feature properties:  
    X: [41 42 43]  
    Y: [1 2 3]  
    Temperature: [61 62 63]
```

Construct a Mappoint Vector from a Structure Array

Create a structure array and then create a mappoint vector, specifying the array as input.

```
structArray = shaperead('boston_placenames')  
p = mappoint(structArray)
```

```
structArray =
```

```
13x1 struct array with fields:  
    Geometry  
    X  
    Y  
    NAME  
    FEATURE  
    COORD
```

```
p =  
  
13x1 mappoint vector with properties:  
  
Collection properties:  
  Geometry: 'point'  
  Metadata: [1x1 struct]  
Feature properties:  
  X: [1x13 double]  
  Y: [1x13 double]  
  NAME: {1x13 cell}  
  FEATURE: {1x13 cell}  
  COORD: {1x13 cell}
```

Construct a Mappoint Vector from X and Y Numeric Arrays and a Structure Array

```
[structArray, A] = shaperead('boston_placenames');  
x = [structArray.X];  
y = [structArray.Y];  
p = mappoint(x, y, A)
```

```
p =  
  
13x1 mappoint vector with properties:  
  
Collection properties:  
  Geometry: 'point'  
  Metadata: [1x1 struct]  
Feature properties:  
  X: [1x13 double]  
  Y: [1x13 double]  
  NAME: {1x13 cell}  
  FEATURE: {1x13 cell}  
  COORD: {1x13 cell}
```

Construct a Mappoint Vector for One Feature

This example shows how to add a single feature to an empty mappoint vector after construction.

```
x = 1;
y = 1;
p = mappoint(x, y)

p =

1x1 mappoint vector with properties:

Collection properties:
    Geometry: 'point'
    Metadata: [1x1 struct]
Feature properties:
    X: 1
    Y: 1
```

Add a dynamic Feature property with a character vector value.

```
p.FeatureName = 'My Feature'

p =

1x1 mappoint vector with properties:

Collection properties:
    Geometry: 'point'
    Metadata: [1x1 struct]
Feature properties:
    X: 1
    Y: 1
    FeatureName: 'My Feature'
```

Construct a Mappoint Vector for Multiple Features and Examine Autosizing

This example show how mappoint vectors autoresize all properties lengths to ensure they are equal in size when a new dynamic property is added or an existing property is appended or shortened.

Create a mappoint vector.

```
x = [1 2];
y = [10 10];
p = mappoint(x,y)
```

```
p =  
  
2x1 mappoint vector with properties:  
  
Collection properties:  
    Geometry: 'point'  
    Metadata: [1x1 struct]  
Feature properties:  
    X: [1 2]  
    Y: [10 10]
```

Add a dynamic Feature property.

```
p.FeatureName = {'Feature 1', 'Feature 2'}  
  
p =  
  
2x1 mappoint vector with properties:  
  
Collection properties:  
    Geometry: 'point'  
    Metadata: [1x1 struct]  
Feature properties:  
    X: [1 2]  
    Y: [10 10]  
    FeatureName: {'Feature 1' 'Feature 2'}
```

Add a numeric dynamic Feature property.

```
p.ID = [1 2]  
  
p =  
  
2x1 mappoint vector with properties:  
  
Collection properties:  
    Geometry: 'point'  
    Metadata: [1x1 struct]  
Feature properties:  
    X: [1 2]  
    Y: [10 10]  
    FeatureName: {'Feature 1' 'Feature 2'}  
    ID: [1 2]
```

Add a third feature. All properties are autosized so that all vector lengths match.

```
p(3).X = 3
p(3).Y = 10
```

```
p =
```

```
3x1 mappoint vector with properties:
```

```
Collection properties:
```

```
    Geometry: 'point'
```

```
    Metadata: [1x1 struct]
```

```
Feature properties:
```

```
    X: [1 2 3]
```

```
    Y: [10 10 10]
```

```
    FeatureName: {'Feature 1' 'Feature 2' ''}
```

```
    ID: [1 2 0]
```

Set the values for the ID feature dynamic property with more values than contained in X or Y. All properties are expanded to match in size.

```
p.ID = 1:4
```

```
p =
```

```
4x1 mappoint vector with properties:
```

```
Collection properties:
```

```
    Geometry: 'point'
```

```
    Metadata: [1x1 struct]
```

```
Feature properties:
```

```
    X: [1 2 3 0]
```

```
    Y: [10 10 10 0]
```

```
    FeatureName: {'Feature 1' 'Feature 2' '' ''}
```

```
    ID: [1 2 3 4]
```

Set the values for the ID dynamic Feature property with fewer values than contained in X or Y. The ID property values expand to match the length of X and Y.

```
p.ID = 1:2
```

```
p =
```

```
4x1 mappoint vector with properties:
```

```
Collection properties:
```

```
    Geometry: 'point'
```

```
Metadata: [1x1 struct]
Feature properties:
  X: [1 2 3 0]
  Y: [10 10 10 0]
FeatureName: {'Feature 1' 'Feature 2' '' ''}
ID: [1 2 0 0]
```

Set the values of either coordinate property (X or Y) with fewer values. All properties shrink in size to match the new length.

```
p.X = 1:2
```

```
p =
```

```
2x1 mappoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  X: [1 2]
  Y: [10 10]
FeatureName: {'Feature 1' 'Feature 2'}
ID: [1 2]
```

Remove the FeatureName property by setting its value to [].

```
p.FeatureName = []
```

```
p =
```

```
2x1 mappoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  X: [1 2]
  Y: [10 10]
ID: [1 2]
```

Remove all dynamic properties and set the object to empty by setting a coordinate property value to [].

```
p.X = []
```



```

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  X: []
  Y: []

```

Construct a Mappoint Specifying Two Features

This example shows how to include multiple dynamic features during object construction.

```

point = mappoint([42 44],[10, 11], 'Temperature', [63 65], 'TemperatureUnits', 'Fahrenheit'
point =

```

2x1 mappoint vector with properties:

```

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  X: [42 44]
  Y: [10 11]
  Temperature: [63 65]
TemperatureUnits: 'Fahrenheit'

```

Create a Mappoint Vector from a MAT-File

This example shows how to construct a mappoint vector using data from a MAT-file containing oceanic depths.

Load data from the seamount MAT-file and construct a mappoint vector to hold the coordinates.

```

seamount = load('seamount');
p = mappoint(seamount.x, seamount.y, 'Z', seamount.z);

```

Create a level list to use to bin the z values and create a list of color values for each level.

```

levels = [unique(floor(seamount.z/1000)) * 1000; 0];
colors = {'red', 'green', 'blue', 'cyan', 'black'};

```

Add a `MinLevel` and `MaxLevel` feature property to indicate the lowest and highest binned level. Add a dynamic feature property to indicate the z-coordinate. Add a dynamic Feature property to indicate a binned level value and a color value for a given level. Include metadata information from the MAT-file.

```
for k = 1:length(levels) - 1
    index = levels(k) <= p.Z & p.Z < levels(k+1);
    p(index).MinLevel = levels(k);
    p(index).MaxLevel = levels(k+1) - 1;
    p(index).Color = colors{k};
end
```

Add metadata information. `Metadata` is a scalar structure containing information for the entire set of properties. You can add any type of data to the structure.


```
p.Metadata.Caption = seamount.caption;
p.Metadata
```

```
ans =
```

```
    Caption: [1x229 char]
```


Display the point data as a 2-D plot.

```
figure
minLevels = unique(p.MinLevel);
for k=1:length(minLevels)
    index = p.MinLevel == minLevels(k);
    mapshow(p(index).X, p(index).Y, ...
        'MarkerEdgeColor', p(find(index,1)).Color, ...
        'Marker', 'o', ...
        'DisplayType', 'point')
end
legend(num2str(minLevels'))
```



Display the point data as a 3-D scatter plot.

```
figure  
scatter3(p.X, p.Y, p.Z)
```



Assign Dynamic Features to Mappoint Vector from a Structure Array

This example shows how to create a mappoint vector from a structure array, and how to add features and metadata to the mappoint vector.

```
structArray = shaperead('boston_placenames');  
p = mappoint();  
p.X = [structArray.X];  
p.Y = [structArray.Y];  
p.Name = {structArray.NAME}  
  
p =
```

13x1 mappoint vector with properties:

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  X: [1x13 double]
  Y: [1x13 double]
  Name: {1x13 cell}
```

Construct a mappoint vector from a structure array using the constructor syntax.

```
filename = 'boston_placenames.shp';
structArray = shaperead(filename);
p = mappoint(structArray)
```

p =

13x1 mappoint vector with properties:

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  X: [1x13 double]
  Y: [1x13 double]
  NAME: {1x13 cell}
  FEATURE: {1x13 cell}
  COORD: {1x13 cell}
```

Add a Filename field to the Metadata structure. Display the first five points and the Metadata structure.

```
p.Metadata.Filename = filename;
p(1:5)
p.Metadata
```

ans =

5x1 mappoint vector with properties:

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
```

```
X: [2.3403e+05 2.3357e+05 2.3574e+05 2.3627e+05 2.3574e+05]
Y: [900038 9.0019e+05 9.0113e+05 9.0097e+05 9.0036e+05]
NAME: {1x5 cell}
FEATURE: {'PPL-SUBDVSN' ' MARSH' ' HILL' ' PPL' ' PENINSULA'}
COORD: {1x5 cell}
```

ans =

```
Filename: 'boston_placenames.shp'
```

Append a Point by Indexing

This example show how to add a feature to the mappoint vector using linear indexing.

Append Paderborn, Germany to the vector of world cities.

```
p = mappoint(shaperead('worldcities.shp'));
x = 51.715254;
y = 8.75213;
p = append(p, x, y, 'Name', 'Paderborn');
p(end)
```

ans =

```
1x1 mappoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  X: 51.7153
  Y: 8.7521
  Name: 'Paderborn'
```

You can also add a point to the end of the mappoint vector using linear indexing. Add Arlington, Virginia to the end of the vector.

```
p(end+1).X = 38.880043;
p(end).Y = -77.196676;
p(end).Name = 'Arlington';
p(end-1:end)
```

ans =

2x1 mappoint vector with properties:

Collection properties:

Geometry: 'point'

Metadata: [1x1 struct]

Feature properties:

X: [51.7153 38.8800]


Y: [8.7521 -77.1967]

Name: {'Paderborn' 'Arlington'}

% Plot the points

figure

mapshow(p.X, p.Y, 'DisplayType', 'point')



Sort Dynamic Properties

This example show how features can be sorted by using the indexing behavior of the mappoint class.

Construct a mappoint vector and sort the dynamic properties.

```
p = mappoint(shaperead('tsunamis'));  
p = p(:, sort(fieldnames(p)))  
  
p =
```


162x1 mappoint vector with properties:

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  X: [1x162 double]
  Y: [1x162 double]
  Cause: {1x162 cell}
  Cause_Code: [1x162 double]
  Country: {1x162 cell}
  Day: [1x162 double]
  Desc_Deaths: [1x162 double]
  Eq_Mag: [1x162 double]
  Hour: [1x162 double]
  Iida_Mag: [1x162 double]
  Intensity: [1x162 double]
  Location: {1x162 cell}
  Max_Height: [1x162 double]
  Minute: [1x162 double]
  Month: [1x162 double]
  Num_Deaths: [1x162 double]
  Second: [1x162 double]
  Val_Code: [1x162 double]
  Validity: {1x162 cell}
  Year: [1x162 double]
```

Modify the mappoint vector to contain only the dynamic properties, 'Year', 'Month', 'Day', 'Hour', 'Minute'.

```
p = p(:, {'Year', 'Month', 'Day', 'Hour', 'Minute'})
```

```
p =
```

162x1 mappoint vector with properties:

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  X: [1x162 double]
  Y: [1x162 double]
  Year: [1x162 double]
  Month: [1x162 double]
  Day: [1x162 double]
```

```
Hour: [1x162 double]
Minute: [1x162 double]
```

Display the first five elements.

```
p(1:5)
```

```
ans =
```

```
5x1 mappoint vector with properties:
```

```
Collection properties:
```

```
Geometry: 'point'
```

```
Metadata: [1x1 struct]
```

```
Feature properties:
```

```
X: [128.3000 -156 157.9500 143.8500 -155]
```

```
Y: [-3.8000 19.5000 -9.0200 42.1500 19.1000]
```

```
Year: [1950 1951 1951 1952 1952]
```

```
Month: [10 8 12 3 3]
```

```
Day: [8 21 22 4 17]
```

```
Hour: [3 10 NaN 1 3]
```

```
Minute: [23 57 NaN 22 58]
```

Row and Column Input Arguments

This example demonstrates that input arguments *x* and *y* can be either row or column vectors.

If you typically store *x*- and *y*-coordinate values in an *n*-by-2 or 2-by-*m* array, you can assign a mappoint object to these numeric values. If the values are stored in an *n*-by-2 array, then the X property values are assigned to the first column and the Y property values are assigned to the second column.

```
x = 1:10;
y = 21:30;
pts = [x' y'];
p = mappoint;
p(1:length(pts)) = pts
```

```
p =
```

```
10x1 mappoint vector with properties:
```

```

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  X: [1 2 3 4 5 6 7 8 9 10]
  Y: [21 22 23 24 25 26 27 28 29 30]

```

If the values are stored in a 2-by- m array, then the X property values are assigned to the first row and the Y property values are assigned to the second row.

```

pts = [x; y];
p(1:length(pts)) = pts

```

```
p =
```

```
10x1 mappoint vector with properties:
```

```

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  X: [1 2 3 4 5 6 7 8 9 10]
  Y: [21 22 23 24 25 26 27 28 29 30]

```

Observe that in both cases, X and Y are stored as row vectors.

Definitions

Collection Properties

Collection properties contain only one value per class instance. In contrast, the Feature property type has attribute values associated with each feature. `Geometry` and `Metadata` are the only two Collection properties.

Feature Properties

Feature properties contain one value (a scalar number, string scalar, or a character vector) for each feature in a mappoint vector. They are suitable for properties such as name, owner, serial number, or age, that describe a given feature (an element of a mappoint vector) as a whole. The X and Y coordinate properties are feature properties as there is one value for each element in the mappoint vector.

Feature properties can be added dynamically using dot notation. This is similar to adding dynamic fields to a structure.

Tips

- If X, Y, or a dynamic property is set with more values than features in the mappoint vector, then all other properties expand in size using 0 for numeric values and an empty character vector (' ') for cell values.
- If a dynamic property is set with fewer values than the number of features, then this dynamic property expands to match the size of the other properties, by inserting a 0 if the value is numeric or an empty character vector (' '), if the value is a cell array.
- If the X or Y property of the mappoint vector is set with fewer values than contained in the object, then all other properties shrink in size.
- If either X or Y is set to [], then both coordinate properties are set to [] and all dynamic properties are removed.
- If a dynamic property is set to [], then it is removed from the object.
- The mappoint vector can be indexed like any MATLAB vector. You can access any element of the vector to obtain a specific feature. The following examples demonstrate this behavior:

“Append a Point by Indexing” on page 1-884

“Sort Dynamic Properties” on page 1-886

See Also

Functions

gpxread | shaperead

Objects

geopoint | geoshape | mapshape

Introduced in R2012a

MapPostingsReference

Reference raster postings to map coordinates

Description

A map postings raster reference object encapsulates the relationship between a planar map coordinate system and a system of intrinsic coordinates anchored to the columns and rows of a 2-D spatially referenced grid of point samples (or “postings”).

Typically, the raster is sampled regularly in the planar world x - and world y -coordinates of the map system, such that the intrinsic x and world x axes align and the intrinsic y and world y axes align. When this is true, the relationship between the two systems is rectilinear. More generally, and much more rarely, their relationship is affine. The affine relationship allows for a possible rotation (and skew). In either case, rectilinear or affine, the sample spacing from row to row need not equal the sample spacing from column to column. For more information about coordinate systems, see “Intrinsic Coordinate System” on page 1-896.

Creation

You can use any of the following functions to create a `MapPostingsReference` object to reference a regular raster of posted samples to planar (map) coordinates.

- `maprefpostings` — Create a map raster reference object.
- `maprasterref` — Convert a world file to a map raster reference object.
- `refmatToMapRasterReference` — Convert a referencing matrix to a map raster reference object.

For example, to construct a map raster reference object with default property settings, use this command:

```
R = maprefpostings()
```

```
R =
```

```
MapPostingsReference with properties:
```

```
XWorldLimits: [0.5 2.5]
YWorldLimits: [0.5 2.5]
RasterSize: [2 2]
RasterInterpretation: 'postings'
ColumnsStartFrom: 'south'
RowsStartFrom: 'west'
SampleSpacingInWorldX: 2
SampleSpacingInWorldY: 2
RasterExtentInWorldX: 2
RasterExtentInWorldY: 2
XIntrinsicLimits: [1 2]
YIntrinsicLimits: [1 2]
TransformationType: 'rectilinear'
CoordinateSystemType: 'planar'
```

Properties

XWorldLimits — Limits of raster in world x-coordinates

[0.5 2.5] (default) | two-element row vector

Limits of raster in world x-coordinates, specified as a two-element row vector of the form [xMin xMax].

Example: [207000 209000]

Data Types: double

YWorldLimits — Limits of raster in world y-coordinates

[0.5 2.5] (default) | two-element row vector

Limits of raster in world y-coordinates, specified as a two-element row vector of the form [yMin yMax].

Example: [911000 913000]

Data Types: double

RasterSize — Number of rows and columns of the raster or image associated with the referencing object

[2 2] (default) | two-element vector of positive integers

Number of rows and columns of the raster or image associated with the referencing object, specified as a two-element vector, [m n], where m represents the number of rows

and n the number of columns. For convenience, you can assign a size vector having more than two elements. This enables assignments like `R.RasterSize = size(RGB)`, where `RGB` is m -by- n -by-3. In cases like this, the object stores only the first two elements of the size vector and ignores the higher (nonspatial) dimensions. m and n must be positive in all cases and must be 2 or greater.

Example: `[200 300]`

Data Types: `double`

RasterInterpretation — Geometric nature of the raster

`'postings'` (default)

Geometric nature of the raster, specified as `'postings'`. The value `'postings'` indicates that the raster comprises a grid of sample points, where rows or columns of samples run along the edge of the grid. For an m -by- n raster, points with an intrinsic x -coordinate of 1 or n or an intrinsic y -coordinate of 1 or m fall right on an edge (or corner) of the raster.

Cannot be set.

Data Types: `char`

ColumnsStartFrom — Edge from which column indexing starts

`'south'` (default) | `'north'`

Edge from which column indexing starts, specified as `'south'` or `'north'`.

Example: `ColumnsStartFrom: 'south'`

Data Types: `char`

RowsStartFrom — Edge from which row indexing starts

`'west'` (default) | `'east'`

Edge from which row indexing starts, specified as `'west'` or `'east'`.

Example: `RowsStartFrom: 'east'`

Data Types: `char`

SampleSpacingInWorldX — East-west distance between adjacent postings

2 (default) | positive numeric scalar

East-west distance between adjacent postings, specified as a positive numeric scalar. The value is constant throughout the raster.

Example: 2.5

Data Types: double

SampleSpacingInWorldY — North-south distance between adjacent postings

2 (default) | positive numeric scalar

North-south distance between adjacent postings, specified as a positive numeric scalar. The value is constant throughout the raster.

Example: 2.5

Data Types: double

RasterExtentInWorldX — Extent of the full raster or image as measured in the world system in a direction parallel to its rows

2 (default) | positive numeric scalar

This property is read-only.

Extent of the full raster or image as measured in the world system in a direction parallel to its rows, specified as a positive numeric scalar. In the case of a rectilinear geometry, which is most typical, this is the horizontal direction (east-west).

Data Types: double

RasterExtentInWorldY — Extent of the full raster or image as measured in the world system in a direction parallel to its columns

2 (default) | positive numeric scalar

This property is read-only.

Extent of the full raster or image as measured in the world system in a direction parallel to its columns. In the case of a rectilinear geometry, which is most typical, this is the vertical direction (north-south).

Data Types: double

XIntrinsicLimits — Raster limits in intrinsic x-coordinates

[1 2] (default) | two-element row vector of positive integers

This property is read-only.

Raster limits in intrinsic x-coordinates, specified as a two-element row vector of positive integers, [xMin xMax]. For an m -by- n raster, XIntrinsicLimits equals [1 m], because the RasterInterpretation is 'postings'.

Example: [2 4]

Data Types: double

YIntrinsicLimits — Raster limits in intrinsic y-coordinates

[1 2] (default) | two-element row vector of positive integers

This property is read-only.

Raster limits in intrinsic y-coordinates, specified as a two-element row vector of positive integers, [yMin yMax]. For an m -by- n raster with RasterInterpretation equal to 'postings', YIntrinsicLimits equals [1 m].

Data Types: double

TransformationType — Type of geometric relationship between intrinsic and world systems

'rectilinear' (default) | 'affine'

This property is read-only.

Type of geometric relationship between the intrinsic coordinate system and the world coordinate system, specified as either 'rectilinear' or 'affine'. Its value is 'rectilinear' when world x depends only on intrinsic x and vice versa, and world y depends only on intrinsic y and vice versa. When the value is 'rectilinear', the image displays without rotation in the world system, although it might be flipped. Otherwise, the value is 'affine'.

Data Types: char

CoordinateSystemType — Type of coordinate system to which the image or raster is referenced

'planar' (default)

This property is read-only.

Type of coordinate system to which the image or raster is referenced, specified as 'planar'.

Data Types: char

Object Functions

| | |
|-------------------------------|--|
| <code>contains</code> | Determine if geographic or map raster contains points |
| <code>firstCornerX</code> | Return world x-coordinate of map raster index (1,1) |
| <code>firstCornerY</code> | Return world y-coordinate of map raster index (1,1) |
| <code>intrinsicToWorld</code> | Transform intrinsic to planar world coordinates |
| <code>sizesMatch</code> | Determine if geographic or map raster object and image or raster are size-compatible |
| <code>worldFileMatrix</code> | Return world file parameters for transformation |
| <code>worldToDiscrete</code> | Transform planar world to discrete coordinates |
| <code>worldToIntrinsic</code> | Transform planar world to intrinsic coordinates |

Definitions

Intrinsic Coordinate System

A 2-D Cartesian system with its x -axis running parallel to the rows of a raster or image and its y -axis running parallel to the columns. x increases by 1 from column to column, and y increases by 1 from row to row.

The Mapping Toolbox and Image Processing Toolbox use the convention for the location of the origin relative to the raster cells or sampling points such that, at a sample location or at the center of a cell, x has an integer value equal to the column index. Likewise, at a sample location or at the center of a cell, y has an integer value equal to the row index. For details, see Image Coordinate Systems (Image Processing Toolbox).

See Also

Functions

`maprasterref` | `maprefpostings`

Objects

`GeographicCellsReference` | `GeographicPostingsReference` | `MapCellsReference`

Introduced in R2013b

mapprofile

Interpolate between waypoints on regular data grid

Syntax

```
[zi,ri,lat,lon] = mapprofile
[zi,ri,lat,lon] = mapprofile(Z,R,lat,lon)
[zi,ri,lat,lon] = mapprofile(Z,R,lat,lon,units)
[zi,ri,lat,lon] = mapprofile(Z,R,lat,lon,ellipsoid)
[zi,ri,lat,lon] = mapprofile( ____, 'trackmethod', 'interpmethod')
```

Description

`mapprofile` plots a profile of values between waypoints on a displayed regular data grid. `mapprofile` uses the current object if it is a regular data grid, or the first regular data grid found on the current axes. The grid's `zdata` is used for the profile. The color data is used in the absence of `zdata`. The result is displayed in a new figure.

`[zi,ri,lat,lon] = mapprofile` returns the values of the profile without displaying them. The output `zi` contains interpolated values along great circles between the waypoints. `ri` is a vector of associated distances from the first waypoint in units of degrees of arc along the surface. `lat` and `lon` are the corresponding latitudes and longitudes.

`[zi,ri,lat,lon] = mapprofile(Z,R,lat,lon)` accepts as input a regular data grid and waypoint vectors. No displayed grid is required. Sets of waypoints may be separated by NaNs into line sequences. The output ranges are measured from the first waypoint within a sequence. `R` can be a geographic raster reference object, a referencing vector, or a referencing matrix.

If `R` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z)`.

If `R` is a referencing vector, it must be a 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If *R* is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to or from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If *R* is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel.

`[zi,ri,lat,lon] = mapprofile(Z,R,lat,lon,units)` specifies the units of the output ranges along the profile. Valid range units inputs are any distance value recognized by `unitsratio`. Surface distances are computed using the default radius of the earth. If omitted, 'degrees' are assumed.

`[zi,ri,lat,lon] = mapprofile(Z,R,lat,lon,ellipsoid)` uses the provided ellipsoid definition in computing the range along the profile. `ellipsoid` is a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. The output range is reported in the same distance units as the semimajor axes of the ellipsoid. If omitted, the range vector is for a sphere.

`[zi,ri,lat,lon] = mapprofile(___, 'trackmethod', 'interpmethod')` control the interpolation methods used. Valid track methods are 'gc' for great circle tracks between waypoints, and 'rh' for rhumb lines. Valid methods for interpolation within the matrix are 'bilinear' for linear interpolation, 'bicubic' for cubic interpolation, and 'nearest' for nearest neighbor interpolation. If omitted, 'gc' and 'bilinear' are assumed.

Examples

Example 1


Create a map axes for the Korean peninsula. Specify an elevation profile across the sample Korean digital elevation data and plot it, combined with a coastline and city markers:

```
load korea
h = worldmap(map, refvec); % The figure has no map content.
plat = [ 43  43  41  38];
plon = [116 120 126 128];
```

```

mapprofile(map, refvec, plat, plon)
load coastlines
plotm(coastlat,coastlon)
geoshow('worldcities.shp', 'Marker', '.', 'Color', 'red')

```




When you select more than two waypoints, the automatically generated figure displays the result in three dimensions. The following example shows the relative sizes of the mountains in northern China compared to the depths of the Sea of Japan. The call to `mapprofile` without input arguments enables you to interactively pick waypoints on the figure using the mouse. Each click selects a new waypoint and stores the profile values, but the points are not displayed on the figure. Press **Enter** after you select the final point:

```


axes(h);
meshm(map, refvec, size(map))
demcmap(map)
[zi,ri,lat,lon] = mapprofile;

```

Adding output arguments suppresses the display of the results in a new figure. You can then use the results in further calculations or display the results yourself. Here the profile from the upper left to lower right is computed from waypoints interactively picked on the map (your profile will not be identical to what is shown below). The example converts ranges and elevations to kilometers and displays them in a new figure, setting the vertical exaggeration factor to 20. With no vertical exaggeration, the changes in elevation would be almost too small to see.



```
figure
plot(deg2km(ri),zi/1000)
daspect([ 1 1/20 1 ]);
xlabel 'Range (km)'
ylabel 'Elevation (km)'
```



Naturally, the profile you get depends on the transect locations you pick.

Example 2

You can compute values along a path without reference to an existing figure by providing a regular data grid and vectors of waypoint coordinates. Optional arguments allow control over the units of the range output and interpolation methods between waypoints and data grid elements.


Show what land and ocean areas lie under a great circle track from Frankfurt to Seattle:

```
cities = shaperead('worldcities.shp', 'UseGeoCoords', true);
Seattle = strcmp('Seattle', {cities(:).Name});
```

```

Frankfurt = strcmp('Frankfurt', {cities(:).Name});
lat = [cities(Seattle).Lat cities(Frankfurt).Lat]
lon = [cities(Seattle).Lon cities(Frankfurt).Lon]
load topo
[valp,rp,latp,lonp] = ...
    mapprofile(double(topo),topolegend, ...
        lat,lon,'km','gc','nearest');
figure
worldmap([40 80],[-135 20])
land = shaperead('landareas.shp', 'UseGeoCoords', true);
faceColors = makesymbolspec('Polygon',...
    {'INDEX', [1 numel(land)], 'FaceColor', ...
        polcmap(numel(land))});
geoshow(land,'SymbolSpec',faceColors)
plotm(latp,lonp,'r')
plotm(lat,lon,'ro')
axis off

```



See Also

los2 | ltltn2val

maprasterref

Construct map raster reference object

Note Use the `maprefcells` function or the `maprefpostings` function instead, except when constructing a raster reference object from world file input.

Syntax

`R = maprasterref()`

`R = maprasterref(Name, Value)`

`R = maprasterref(W, rasterSize, rasterInterpretation)`

Description

`R = maprasterref()` constructs a map raster reference object with default property values.

`R = maprasterref(Name, Value)` accepts a list of name-value pairs that are used to assign selected properties when initializing a map raster reference object.

`R = maprasterref(W, rasterSize, rasterInterpretation)` constructs a map raster reference object with the specified raster size and interpretation properties, and with remaining properties defined by a 2-by-3 world file matrix, `W`.

Input Arguments

W — World file matrix

2-by-3 numeric array

World file matrix, specified as a 2-by-3 numeric array. Each of the six elements in `W` matches one of the lines in a world file that defines the transformation in raster referencing object `R`.

Data Types: `double`

rasterSize — Number of rows and columns of the raster

two-element vector

Number of rows (m) and columns (n) of the raster or image associated with the referencing object, specified as a two-element vector $[m\ n]$. For convenience, you may assign a size vector having more than two elements to `RasterSize`. This flexibility enables assignments like `R.RasterSize = size(RGB)`, for example, where `RGB` is m -by- n -by-3. However, in such cases, only the first two elements of the size vector are actually stored. The higher (non-spatial) dimensions are ignored

rasterInterpretation — Control to handle raster edges

'cells' (default) | 'postings'

Controls handling of raster edges. The `rasterInterpretation` input is optional, and can equal either 'cells' or 'postings'.

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

You can include any of the following properties, overriding their default values as needed. Alternatively, you may omit any or all properties when constructing your map raster reference object. Then, you can customize the result by resetting properties from this list one at a time. This name-value syntax always results in an object with a 'rectilinear' `TransformationType`. If your image is rotated with respect to the world coordinate axes, you need an object with a `TransformationType` of 'affine'. Alternately, you can provide an appropriate world file matrix as input, as shown in the third syntax. You cannot do it by resetting properties of an existing rectilinear map raster reference object.

XLimWorldLimits of raster in world x Two-element row vector of the form $[xMin\ xMax]$.**Default:** [0.5 2.5]

YLimWorld

Limits of raster in world *y*

Two-element row vector of the form [yMin yMax].

Default: [0.5 2.5]

RasterSize

Two-element vector [M N] specifying the number of rows (*M*) and columns (*N*) of the raster or image associated with the referencing object. For convenience, you may assign a size vector having more than two elements to `RasterSize`. This flexibility enables assignments like `R.RasterSize = size(RGB)`, for example, where `RGB` is *M*-by-*N*-by-3. However, in such cases, only the first two elements of the size vector are actually stored. The higher (non-spatial) dimensions are ignored.

Default: [2 2]

RasterInterpretation

Controls handling of raster edges, specified as either 'cells' or 'postings'.

Default: 'cells'

ColumnsStartFrom

Edge where column indexing starts, specified as either 'south' or 'north'.

Default: 'south'

RowsStartFrom

Edge from which row indexing starts, specified as either 'west' or 'east'.

Default: 'west'

Output Arguments

R — Map raster

MapCellsReference or MapPostingsReference object

Map raster, specified as a `MapCellsReference` or `MapPostingsReference` object.

Examples

Construct Raster Referencing Object Specifying Limits

Construct a referencing object for an 1000-by-2000 image with square, half-meter pixels referenced to a planar map coordinate system (the "world" system). The X-limits in the world system are 207000 and 208000. The Y-limits are 912500 and 913000. The image follows the popular convention in which world X increases from column to column and world Y decreases from row to row.

```
R = maprasterref('RasterSize', [1000 2000], ...
                'YWorldLimits', [912500 913000], 'ColumnsStartFrom', 'north', ...
                'XWorldLimits', [207000 208000])
```

```
R =
  MapCellsReference with properties:
```

```

    XWorldLimits: [207000 208000]
    YWorldLimits: [912500 913000]
    RasterSize: [1000 2000]
  RasterInterpretation: 'cells'
    ColumnsStartFrom: 'north'
    RowsStartFrom: 'west'
  CellExtentInWorldX: 1/2
  CellExtentInWorldY: 1/2
  RasterExtentInWorldX: 1000
  RasterExtentInWorldY: 500
    XIntrinsicLimits: [0.5 2000.5]
    YIntrinsicLimits: [0.5 1000.5]
  TransformationType: 'rectilinear'
  CoordinateSystemType: 'planar'
```

Construct Default Raster Reference Object and Set Fields

Create a default raster reference object.

R = `maprasterref`

R =

MapCellsReference with properties:

```
XWorldLimits: [0.5 2.5]
YWorldLimits: [0.5 2.5]
RasterSize: [2 2]
RasterInterpretation: 'cells'
ColumnsStartFrom: 'south'
RowsStartFrom: 'west'
CellExtentInWorldX: 1
CellExtentInWorldY: 1
RasterExtentInWorldX: 2
RasterExtentInWorldY: 2
XIntrinsicLimits: [0.5 2.5]
YIntrinsicLimits: [0.5 2.5]
TransformationType: 'rectilinear'
CoordinateSystemType: 'planar'
```

Set fields in the raster reference object.

```
R.XWorldLimits = [207000 208000];
R.YWorldLimits = [912500 913000];
R.ColumnsStartFrom = 'north';
R.RasterSize = [1000 2000]
```

R =

MapCellsReference with properties:

```
XWorldLimits: [207000 208000]
YWorldLimits: [912500 913000]
RasterSize: [1000 2000]
RasterInterpretation: 'cells'
ColumnsStartFrom: 'north'
RowsStartFrom: 'west'
CellExtentInWorldX: 1/2
CellExtentInWorldY: 1/2
RasterExtentInWorldX: 1000
RasterExtentInWorldY: 500
XIntrinsicLimits: [0.5 2000.5]
YIntrinsicLimits: [0.5 1000.5]
TransformationType: 'rectilinear'
```

```
CoordinateSystemType: 'planar'
```

Construct Raster Reference Object Using World File Matrix

Create a world file matrix.

```
W = [0.5    0.0   207000.25; ...  
     0.0   -0.5   912999.75];
```

Specify the size of the image.

```
rasterSize = [1000 2000];
```

Create the map raster reference object.

```
R = maprasterref(W, rasterSize)
```

```
R =
```

```
MapCellsReference with properties:
```

```
    XWorldLimits: [207000 208000]  
    YWorldLimits: [912500 913000]  
    RasterSize: [1000 2000]  
    RasterInterpretation: 'cells'  
    ColumnsStartFrom: 'north'  
    RowsStartFrom: 'west'  
    CellExtentInWorldX: 1/2  
    CellExtentInWorldY: 1/2  
    RasterExtentInWorldX: 1000  
    RasterExtentInWorldY: 500  
    XIntrinsicLimits: [0.5 2000.5]  
    YIntrinsicLimits: [0.5 1000.5]  
    TransformationType: 'rectilinear'  
    CoordinateSystemType: 'planar'
```

See Also

Functions

[georasterref](#) | [maprefcells](#) | [maprefpostings](#) | [worldFileMatrix](#)

Objects

[MapCellsReference](#) | [MapPostingsReference](#)

maprefcells

Reference raster cells to map coordinates

Syntax

```
R = maprefcells()  
R = maprefcells(xWorldLimits,yWorldLimits,rasterSize)  
R = maprefcells(xWorldLimits,yWorldLimits,cellExtentInWorldX,  
cellExtentInWorldY)  
R = maprefcells(xWorldLimits,yWorldLimits, ____,Name,Value)
```

Description

`R = maprefcells()` returns a default referencing object for a regular raster of cells in planar (map) coordinates.

`R = maprefcells(xWorldLimits,yWorldLimits,rasterSize)` constructs a referencing object for a raster of cells spanning the specified limits in planar coordinates, with the numbers of rows and columns specified by `rasterSize`.

`R = maprefcells(xWorldLimits,yWorldLimits,cellExtentInWorldX,cellExtentInWorldY)` allows the cell extents to be set precisely. If necessary, `maprefcells` adjusts the limits of the raster slightly to ensure an integer number of cells in each dimension.

`R = maprefcells(xWorldLimits,yWorldLimits, ____,Name,Value)` allows the directions of the columns and rows to be specified via name-value pairs.

Examples

Construct Referencing Object with Raster Interpretation of Cells

Define latitude and longitude limits and dimensions of the image. The image follows the popular convention in which world x coordinates increase from column to column and world y coordinates decrease from row to row.

```
xWorldLimits = [207000 208000];  
yWorldLimits = [912500 913000];  
rasterSize = [1000 2000]
```

```
rasterSize = 1x2  
            1000    2000
```

Create the referencing object specifying the raster size.

```
R = maprefcells(xWorldLimits,yWorldLimits,rasterSize,...  
              'ColumnsStartFrom','north')
```

```
R =  
MapCellsReference with properties:  
    XWorldLimits: [207000 208000]  
    YWorldLimits: [912500 913000]  
    RasterSize: [1000 2000]  
    RasterInterpretation: 'cells'  
    ColumnsStartFrom: 'north'  
    RowsStartFrom: 'west'  
    CellExtentInWorldX: 1/2  
    CellExtentInWorldY: 1/2  
    RasterExtentInWorldX: 1000  
    RasterExtentInWorldY: 500  
    XIntrinsicLimits: [0.5 2000.5]  
    YIntrinsicLimits: [0.5 1000.5]  
    TransformationType: 'rectilinear'  
    CoordinateSystemType: 'planar'
```

Obtain the same result by specifying the cell extents. For this example, the pixels are 1/2 meter square, referenced to a planar map coordinate system (the "world" system).

```
extent = 1/2;
```



```
R = maprefcells(xWorldLimits,yWorldLimits,extent,extent,...
  'ColumnsStartFrom','north')
```

```
R =
  MapCellsReference with properties:

      XWorldLimits: [207000 208000]
      YWorldLimits: [912500 913000]
      RasterSize: [1000 2000]
  RasterInterpretation: 'cells'
      ColumnsStartFrom: 'north'
      RowsStartFrom: 'west'
  CellExtentInWorldX: 1/2
  CellExtentInWorldY: 1/2
  RasterExtentInWorldX: 1000
  RasterExtentInWorldY: 500
      XIntrinsicLimits: [0.5 2000.5]
      YIntrinsicLimits: [0.5 1000.5]
  TransformationType: 'rectilinear'
  CoordinateSystemType: 'planar'
```

Input Arguments

xWorldLimits — Limits in the x direction

[0.5 2.5] (default) | 1-by-2 numeric vector

Limits in the x direction, specified as a 1-by-2 numeric vector.

Example: `xWorldLimits = [207000 208000];`

Data Types: double

yWorldLimits — Limits in the y direction

[0.5 2.5] (default) | 1-by-2 numeric vector

Limits in the y direction, specified as a 1-by-2 numeric vector.

Example: `yWorldLimits = [912500 913000];`

Data Types: double

rasterSize — Size of the raster

[2 2] (default) | 1-by-2 numeric vector

Size of the raster, specified as a 1-by-2 numeric vector.

Example: `rasterSize = [180 360];`

Data Types: double

cellExtentInWorldX — Height of cells

1 (default) | numeric scalar

Height of cells, specified as a numeric scalar.

Example: `extent = 1.5`

Data Types: double

cellExtentInWorldY — Width of cells

1 (default) | numeric scalar

Width of cells, specified as a numeric scalar.

Example: `extent = 1.5`

Data Types: double

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

Example: `R = maprefcells(latlim, lonlim, rasterSize, 'ColumnsStartFrom', 'north')`

ColumnsStartFrom — Edge from which column indexing starts

'south' (default) | 'north'

Edge from which column indexing starts, specified as 'north' or 'south'.

Example: `R = maprefcells(latlim, lonlim, rasterSize, 'ColumnsStartFrom', 'north')`

Data Types: char | string

RowsStartFrom — Edge from which row indexing starts`'west' (default) | 'east'`

Edge from which column indexing starts, specified as 'west' or 'east'.

Example: `R =`

```
maprefcells(latlim, lonlim, rasterSize, 'RowsStartFrom', 'east')
```

Data Types: `char | string`

Output Arguments

R — Object that references raster cells to map coordinates

`MapCellsReference` raster reference object

Object that references raster cells to map coordinates, returned as a `MapCellsReference` raster reference object.

Tips

- To construct a map raster reference object from a world file matrix, use the `maprasterref` function.

See Also

`MapCellsReference` | `georefcells` | `maprefpostings`

Introduced in R2015b

maprefpostings

Reference raster postings to map coordinates

Syntax

```
R = maprefpostings()  
R = maprefpostings(xWorldLimits,yWorldLimits,rasterSize)  
R = maprefpostings(xWorldLimits,yWorldLimits,sampleSpacingInWorldX,  
sampleSpacingInWorldY)  
R = maprefpostings(xWorldLimits,yWorldLimits, ____, Name,Value)
```

Description

`R = maprefpostings()` returns a default referencing object for a raster of regularly posted samples in planar (map) coordinates.

`R = maprefpostings(xWorldLimits,yWorldLimits,rasterSize)` constructs a referencing object for a raster spanning the specified limits in planar coordinates, with the numbers of rows and columns specified by `rasterSize`.

`R = maprefpostings(xWorldLimits,yWorldLimits,sampleSpacingInWorldX,sampleSpacingInWorldY)` allows the sample spacings to be set precisely. If necessary, `maprefpostings` adjusts the limits of the raster slightly to ensure an integer number of samples in each dimension.

`R = maprefpostings(xWorldLimits,yWorldLimits, ____, Name,Value)` allows the directions of the columns and rows to be specified via name-value pairs.

Examples

Construct Referencing Object for Grid

Define latitude and longitude limits and dimension of a grid. The example uses postings separated by 1/2 meter, referenced to a planar map coordinate system (the "world" system).

```
xWorldLimits = [207000 208000];
yWorldLimits = [912500 913000];
rasterSize = [1001 2001]
```

```
rasterSize = 1x2
            1001    2001
```

Create the referencing object specifying the raster size.

```
R = maprefpostings(xWorldLimits,yWorldLimits,rasterSize)
```

```
R =
  MapPostingsReference with properties:
        XWorldLimits: [207000 208000]
        YWorldLimits: [912500 913000]
        RasterSize: [1001 2001]
  RasterInterpretation: 'postings'
    ColumnsStartFrom: 'south'
    RowsStartFrom: 'west'
  SampleSpacingInWorldX: 1/2
  SampleSpacingInWorldY: 1/2
  RasterExtentInWorldX: 1000
  RasterExtentInWorldY: 500
    XIntrinsicLimits: [1 2001]
    YIntrinsicLimits: [1 1001]
  TransformationType: 'rectilinear'
  CoordinateSystemType: 'planar'
```

Obtain the same result by specifying the sample spacing.

```
spacing = 1/2;
R = maprefpostings(xWorldLimits,yWorldLimits,spacing,spacing)
```

```
R =
  MapPostingsReference with properties:
      XWorldLimits: [207000 208000]
      YWorldLimits: [912500 913000]
      RasterSize: [1001 2001]
      RasterInterpretation: 'postings'
      ColumnsStartFrom: 'south'
      RowsStartFrom: 'west'
      SampleSpacingInWorldX: 1/2
      SampleSpacingInWorldY: 1/2
      RasterExtentInWorldX: 1000
      RasterExtentInWorldY: 500
      XIntrinsicLimits: [1 2001]
      YIntrinsicLimits: [1 1001]
      TransformationType: 'rectilinear'
      CoordinateSystemType: 'planar'
```

Input Arguments

xWorldLimits — Limits in the x direction

[0.5 2.5] (default) | 1-by-2 numeric vector

Limits in the x direction, specified as a 1-by-2 numeric vector.

Example: `xWorldLimits = [207000 208000];`

Data Types: double

yWorldLimits — Limits in the y direction

[0.5 2.5] (default) | 1-by-2 numeric vector

Limits in the y direction, specified as a 1-by-2 numeric vector.

Example: `yWorldLimits = [912500 913000];`

Data Types: double

rasterSize — Size of the raster

[2 2] (default) | 1-by-2 numeric vector

Size of the raster, specified as a 1-by-2 numeric vector.

Example: `rasterSize = [180 360];`

Data Types: double

sampleSpacingInWorldX — Vertical spacing of posting

1 (default) | numeric scalar

Vertical spacing of posting, specified as a numeric scalar.

Example: `spacing = 1.5`

Data Types: double

sampleSpacingInWorldY — Horizontal spacing of postings

1 (default) | numeric scalar

Horizontal spacing of postings, specified as a numeric scalar.

Example: `spacing = 1.5`

Data Types: double

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

Example: `R = maprefpostings(latlim, lonlim, rasterSize, 'ColumnsStartFrom', 'north')`

ColumnsStartFrom — Edge from which column indexing starts

'south' (default) | 'north'

Edge from which column indexing starts, specified as 'north' or 'south'.

Example: `R = maprefpostings(latlim, lonlim, rasterSize, 'ColumnsStartFrom', 'north')`

Data Types: char | string

RowsStartFrom — Edge from which row indexing starts

'west' (default) | 'east'

Edge from which row indexing starts, specified as 'east' or 'west'.

Example: R =

```
maprefpostings(latlim, lonlim, rasterSize, 'RowsStartFrom', 'east')
```

Data Types: char | string

Output Arguments

R — Object that references raster postings to map coordinates

MapPostingsReference raster reference object

Object that references raster postings to map coordinates, returned as a MapPostingsReference raster reference object.

Tips

- To construct a map raster reference object from a world file matrix, use the `maprasterref` function.

See Also

MapPostingsReference | georefpostings | maprefcells

Introduced in R2015b

maps

List available map projections and verify names

Syntax

```
strmat = maps('namelist')  
strmat = maps('idlist')  
stdstr = maps('proj_id_abbrev')
```

Description

maps displays in the Command Window a table describing all projections available for use.

`strmat = maps('namelist')` returns the English names for the available projections as a matrix of character vectors.

`strmat = maps('idlist')` returns the standard projection identifiers for the available projections as a matrix of character vectors.

`stdstr = maps('proj_id_abbrev')` returns the specific standard projection identification associated with a unique abbreviation.

Examples

To show the first five entries of the projections name list,

```
str1 = maps('namelist');  
str1(1:5,:)  
ans =  
Balthasart Cylindrical  
Behrmann Cylindrical  
Bolshoi Sovietskii Atlas Mira  
Braun Perspective Cylindrical  
Cassini Cylindrical
```

The corresponding shorthand names are

```
str2 = maps('idlist');
str2(1:5,:)
ans =
balthsrt
behrmann
bsam
braun
cassini
```

These shorthand names can be used, for example, when setting the `axesm` property `MapProjection`.

The functions `setm` and `axesm` recognize unique abbreviations (truncations) of these names. The `maps` function can be used to convert such an abbreviation to the standard ID:

```
stdstr = maps('merc')
stdstr =
mercator
```

When the function name alone is used,

```
maps
```

MapTools Projections

| CLASS | NAME | ID STRING |
|-------------|--------------------------------|-----------|
| Cylindrical | Balthasart Cylindrical | balthsrt |
| Cylindrical | Behrmann Cylindrical | behrmann |
| Cylindrical | Bolshoi Sovietskii Atlas Mira* | bsam |
| Cylindrical | Braun Perspective Cylindrical* | braun |
| Cylindrical | Cassini Cylindrical | cassini |
| Cylindrical | Central Cylindrical* | ccylin |
| Cylindrical | Equal Area Cylindrical | eqacylin |
| Cylindrical | Equidistant Cylindrical | eqdcylin |
| Cylindrical | Gall Isographic | giso... |

The actual result contains all defined projections.

See Also

`axesm` | `setm`

mapshape

Planar shape vector

Description

A mapshape vector is an object that represents planar vector features with either point, line, or polygon topology. The features consist of x - and y -coordinates and associated attributes.

Attributes that vary spatially are termed Vertex properties. These elements of the mapshape vector are coupled such that the length of the x - and y -coordinate property values are always equal in length to any additional dynamic Vertex properties.

Attributes that only pertain to the overall feature (point, line, polygon) are termed Feature properties. Feature properties are not linked to the autosizing mechanism of the Vertex properties. Both property types can be added to a mapshape vector after construction using standard dot (.) notation.

Creation

```
s = mapshape()  
s = mapshape(x,y)  
s = mapshape(x,y,Name,Value)  
s = mapshape(structArray)  
s = mapshape(x,y,structArray)
```

Description

`s = mapshape()` constructs an empty mapshape vector, `s`, with these default property settings.

`s =`

0x1 mapshape vector with properties:

Collection properties:

```
    Geometry: 'line'  
    Metadata: [1x1 struct]  
Vertex properties:  
    X: []  
    Y: []
```

`s` is always a column vector.

`s = mapshape(x,y)` constructs a mapshape vector and sets the X and Y property values equal to vectors `x` and `y`.

`s = mapshape(x,y,Name,Value)` constructs a mapshape vector, then adds dynamic properties to the mapshape vector using `Name, Value` argument pairs. You can specify several name-value pair arguments in any order as `Name1, Value1, . . . , NameN, ValueN`.

`s = mapshape(structArray)` constructs a mapshape vector, assigning the fields of the structure array, `structArray`, as dynamic properties. Field values in `structArray` that are not numeric, logical, string scalars, string arrays, character vectors, cell arrays of character vectors, or cell arrays of numeric, logical, or cell array of character vectors values are ignored.

`s = mapshape(x,y,structArray)` constructs a new mapshape vector, sets the X and Y properties equal to vectors `x` and `y`, and sets dynamic properties from the field values of `structArray`.

Properties

`mapshape` class is a general class that represents a variety of planar features. The class permits features to have more than one vertex and can thus represent lines and polygons in addition to multipoints. For more about the property types in `mapshape`, see “Collection Properties” on page 1-942, “Vertex Properties” on page 1-942, and “Feature Properties” on page 1-943.

Dynamic properties are new features and vertices that are added to a mapshape vector. You can attach dynamic Feature and Vertex properties to a mapshape vector during construction with a `Name, Value` pair or after construction using dot (`.`) notation after construction. This is similar to adding new fields to a structure. For an example of adding dynamic Feature properties, see “Construct a Mapshape Vector with Dynamic Properties” on page 1-925.

Geometry — Shape of all the features in the mapshape vector

'line' (default) | 'point' | 'polygon'

Shape of all the features in the mapshape vector, specified as 'line', 'point', or 'polygon'. As a Collection Property there can be only one value per object instance and its purpose is purely informational. The three allowable values for Geometry do not change class behavior. The class does not provide validation for line or polygon topologies.

Data Types: char | string

Metadata — Information for the entire set of features

scalar structure

Information for all the features, specified as a scalar structure. You can add any data type to the structure. As a Collection Property type, only one instance per object is allowed.

- If Metadata is provided as a dynamic property Name in the constructor, and the corresponding Value is a scalar structure, then Value is copied to the Metadata property. Otherwise, an error is issued.
- If a Metadata field is provided by structArray, and both Metadata and structArray are scalar structures, then the Metadata field value is copied to the Metadata property value. If structArray is a scalar but the Metadata field is not a structure, then an error is issued. If structArray is not scalar, then the Metadata field is ignored.

Data Types: struct

X — Planar x-coordinates

numeric row or column vector

Planar x-coordinates, specified as a numeric row or column vector, stored as a row vector.

Data Types: double | single

Y — Planar y-coordinates

numeric row or column vector

Planar y-coordinates, specified as a numeric row or column vector, stored as a row vector.

Data Types: double | single

Object Functions

| | |
|------------|---|
| append | Append features to geographic or planar vector |
| cat | Concatenate geographic or planar vector |
| disp | Display geographic or planar vector |
| fieldnames | Return dynamic property names of geographic or planar vector |
| isempty | Determine if geographic or planar vector is empty |
| isfield | Determine if dynamic property exists in geographic or planar vector |
| isprop | Determine if property exists in geographic or planar vector |
| length | Return number of elements in geographic or planar vector |
| properties | Return property names of geographic or planar vector |
| rmfield | Remove dynamic property from geographic or planar vector |
| rmprop | Remove property from geographic or planar vector |
| size | Return size of geographic or planar vector |
| struct | Convert geographic or planar vector to scalar structure |
| vertcat | Vertically concatenate geographic or planar vectors |

Examples

Construct a Default Mapshape Vector and Set and Add Properties

Create default mapshape vector.

```
s = mapshape()
```

0x1 mapshape vector with properties:

```
Collection properties:
  Geometry: 'line'
  Metadata: [1x1 struct]
Vertex properties:
  X: []
  Y: []
```

Set the values of the existing X and Y properties and dynamically add the Vertex property Z.

```
s(1).X = 0:45:90;
s(1).Y= [10 10 10];
s(1).Z = [10 20 30]
```

```
s =  
  
1x1 mapshape vector with properties:  
  
Collection properties:  
    Geometry: 'line'  
    Metadata: [1x1 struct]  
Vertex properties:  
    X: [0 45 90]  
    Y: [10 10 10]  
    Z: [10 20 30]
```

Construct a Mapshape Vector Specifying X and Y Values

Create a mapshape vector specifying x and y.

```
x = [40, 50, 60];  
y = [10, 20, 30];  
shape = mapshape(x, y)
```

```
shape =  
  
1x1 mapshape vector with properties:  
  
Collection properties:  
    Geometry: 'line'  
    Metadata: [1x1 struct]  
Vertex properties:  
    X: [40 50 60]  
    Y: [10 20 30]
```

Construct a Mapshape Vector with Dynamic Properties

Create mapshape vector specifying a Name-Value pair.

```
x = 1:10;  
y = 21:30;  
temperature = {61:70};  
shape = mapshape(x, y, 'Temperature', temperature)
```

```
shape =
```

```
1x1 mapshape vector with properties:

Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
Vertex properties:
    X: [1 2 3 4 5 6 7 8 9 10]
    Y: [21 22 23 24 25 26 27 28 29 30]
    Temperature: [61 62 63 64 65 66 67 68 69 70]
```

When `Value` is a cell array containing numeric, logical, or cell array of character vectors, it is designated as a Vertex property. Otherwise the Name-Value pair is designated as being a Feature property.

Construct a Mapshape Vector from a Structure Array

Create structure array and then create mapshape vector with array.

```
structArray = shaperead('concord_roads');
shape = mapshape(structArray)

shape =

609x1 mapshape vector with properties:

Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
Vertex properties:
    (609 features concatenated with 608 delimiters)
    X: [1x5422 double]
    Y: [1x5422 double]
Feature properties:
    STREETNAME: {1x609 cell}
    RT_NUMBER: {1x609 cell}
    CLASS: [1x609 double]
    ADMIN_TYPE: [1x609 double]
    LENGTH: [1x609 double]
```


Construct a Mapshape Vector Using Cell Arrays and Structures to Define Multiple Features and Properties

Read data from a shapefile into a structure.

```
[structArray, A] = shaperead('concord_hydro_area');
```

```
structArray =
```

```
98x1 struct array with fields:
```

```
    Geometry  
    BoundingBox  
    X  
    Y
```

```
A =
```

```
98x1 struct array with fields:
```

```
    AREA  
    PERIMETER
```

Create a mapshape vector specifying the structure.

```
shape = mapshape({structArray.X}, {structArray.Y}, A);
```

```
shape.Geometry = structArray(1).Geometry
```

```
shape =
```

```
98x1 mapshape vector with properties:
```

```
Collection properties:
```

```
    Geometry: 'polygon'
```

```
    Metadata: [1x1 struct]
```

```
Vertex properties:
```

```
(98 features concatenated with 97 delimiters)
```

```
    X: [1x4902 double]
```

```
    Y: [1x4902 double]
```

```
Feature properties:
```

```
    AREA: [1x98 double]
```

```
    PERIMETER: [1x98 double]
```

Construct a Mapshape Vector and Add a Feature Property

This example shows how to add a single feature after construction of the mapshape vector using dot (.) notation.

Create a mapshape vector.

```
x = 0:10:100;  
y = 0:10:100;  
shape = mapshape(x, y)
```

shape =

```
1x1 mapshape vector with properties:
```

```
Collection properties:
```

```
    Geometry: 'line'
```

```
    Metadata: [1x1 struct]
```

```
Vertex properties:
```

```
    X: [0 10 20 30 40 50 60 70 80 90 100]
```

```
    Y: [0 10 20 30 40 50 60 70 80 90 100]
```

Add a dynamic Feature property.

```
shape.FeatureName = 'My Feature'
```

shape =

```
1x1 mapshape vector with properties:
```

```
Collection properties:
```

```
    Geometry: 'line'
```

```
    Metadata: [1x1 struct]
```

```
Vertex properties:
```

```
    X: [0 10 20 30 40 50 60 70 80 90 100]
```

```
    Y: [0 10 20 30 40 50 60 70 80 90 100]
```

```
Feature properties:
```

```
    FeatureName: 'My Feature'
```

Add a dynamic Vertex property to the first feature.

```
shape(1).Temperature = [60 61 63 65 66 68 69 70 72 75 80];
```

shape =

```

1x1 mapshape vector with properties:

Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
Vertex properties:
    X: [0 10 20 30 40 50 60 70 80 90 100]
    Y: [0 10 20 30 40 50 60 70 80 90 100]
    Temperature: [60 61 63 65 66 68 69 70 72 75 80]
Feature properties:
    FeatureName: 'My Feature

```

Construct a Mapshape Vector and Manipulate Features

This extended example adds multiple features that are both Vertex and Feature properties. It also demonstrates property behaviors when vector lengths are either changed or set to [].

Create a mapshape vector.

```

x = {1:3, 4:6};
y = {[0 0 0], [1 1 1]};
shape = mapshape(x, y)

```

```

shape =

```

```

2x1 mapshape vector with properties:

Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
Vertex properties:
    (2 features concatenated with 1 delimiter)
    X: [1 2 3 NaN 4 5 6]
    Y: [0 0 0 NaN 1 1 1]

```

Add a two element dynamic Feature property.

```

shape.FeatureName = {'Feature 1', 'Feature 2'}

shape =

```

```
2x1 mapshape vector with properties:
Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
Vertex properties:
(2 features concatenated with 1 delimiter)
    X: [1 2 3 NaN 4 5 6]
    Y: [0 0 0 NaN 1 1 1]
Feature properties:
    FeatureName: {'Feature 1' 'Feature 2'}
```

Add a dynamic Vertex property.

```
z = {101:103, [115, 114, 110]}
shape.Z = z
```

```
z =
    [1x3 double]    [1x3 double]
```

```
shape =
```

```
2x1 mapshape vector with properties:
Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
Vertex properties:
(2 features concatenated with 1 delimiter)
    X: [1 2 3 NaN 4 5 6]
    Y: [0 0 0 NaN 1 1 1]
    Z: [101 102 103 NaN 115 114 110]
Feature properties:
    FeatureName: {'Feature 1' 'Feature 2'}
```

Display the second feature.

```
shape(2)
```

```
ans =
    1x1 mapshape vector with properties:
```

```

Collection properties:
  Geometry: 'line'
  Metadata: [1x1 struct]
Vertex properties:
  X: [4 5 6]
  Y: [1 1 1]
  Z: [115 114 110]
Feature properties:
  FeatureName: 'Feature 2'

```

Add a third feature. The lengths of all the properties are synchronized.

```
shape(3).X = 5:9
```

```
shape =
```

```
3x1 mapshape vector with properties:
```

```

Collection properties:
  Geometry: 'line'
  Metadata: [1x1 struct]
Vertex properties:
  (3 features concatenated with 2 delimiters)
  X: [1 2 3 NaN 4 5 6 NaN 5 6 7 8 9]
  Y: [0 0 0 NaN 1 1 1 NaN 0 0 0 0 0]
  Z: [101 102 103 NaN 115 114 110 NaN 0 0 0 0 0]
Feature properties:
  FeatureName: {'Feature 1' 'Feature 2' ''}

```

Set the values for the Z vertex property with fewer values than contained in X or Y. The Z values expand to match the length of X and Y.

```
shape(3).Z = 1:3
```

```
shape =
```

```
3x1 mapshape vector with properties:
```

```

Collection properties:
  Geometry: 'line'
  Metadata: [1x1 struct]
Vertex properties:
  (3 features concatenated with 2 delimiters)
  X: [1 2 3 NaN 4 5 6 NaN 5 6 7 8 9]
  Y: [0 0 0 NaN 1 1 1 NaN 0 0 0 0 0]

```

```
        Z: [101 102 103 NaN 115 114 110 NaN 1 2 3 0 0]
Feature properties:
  FeatureName: {'Feature 1' 'Feature 2' ''}
```

Set the values for either coordinate property (X or Y) and all properties shrink in size to match the new vertex length of that feature.

```
shape(3).Y = 1
```

```
shape =
```

```
3x1 mapshape vector with properties:
```

```
Collection properties:
```

```
  Geometry: 'line'
```

```
  Metadata: [1x1 struct]
```

```
Vertex properties:
```

```
(3 features concatenated with 2 delimiters)
```

```
  X: [1 2 3 NaN 4 5 6 NaN 5]
```

```
  Y: [0 0 0 NaN 1 1 1 NaN 1]
```

```
  Z: [101 102 103 NaN 115 114 110 NaN 1]
```

```
Feature properties:
```

```
  FeatureName: {'Feature 1' 'Feature 2' ''}
```

Set the values for the Z vertex property with more values than contained in X or Y. All properties expand in length to match Z.

```
shape(3).Z = 1:6
```

```
shape =
```

```
3x1 mapshape vector with properties:
```

```
Collection properties:
```

```
  Geometry: 'line'
```

```
  Metadata: [1x1 struct]
```

```
Vertex properties:
```

```
(3 features concatenated with 2 delimiters)
```

```
  X: [1 2 3 NaN 4 5 6 NaN 5 0 0 0 0 0]
```

```
  Y: [0 0 0 NaN 1 1 1 NaN 1 0 0 0 0 0]
```

```
  Z: [101 102 103 NaN 115 114 110 NaN 1 2 3 4 5 6]
```

```
Feature properties:
```

```
  FeatureName: {'Feature 1' 'Feature 2' ''}
```

Remove the FeatureName property.

```

shape.FeatureName = []

shape =

3x1 mapshape vector with properties:

Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
Vertex properties:
(3 features concatenated with 2 delimiters)
    X: [1 2 3 NaN 4 5 6 NaN 5 0 0 0 0 0]
    Y: [0 0 0 NaN 1 1 1 NaN 1 0 0 0 0 0]
    Z: [101 102 103 NaN 115 114 110 NaN 1 2 3 4 5 6]

```

Remove all dynamic properties and set the object to empty.

```

shape.X = []

shape =

0x1 mapshape vector with properties:

Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
Vertex properties:
    X: []
    Y: []

```

Construct a Mapshape Vector Specifying Several Name-Value Pairs

This example shows how to include multiple dynamic features during object construction.

Create a mapshape vector specifying several name-value pairs.

```

x = {1:3, 4:6};
y = {[0 0 0], [1 1 1]};
z = {41:43, [56 50 59]};
name = {'Feature 1', 'Feature 2'};
id = [1 2];
shape = mapshape(x, y, 'Z', z, 'Name', name, 'ID', id)

```

```
shape =  
  
2x1 mapshape vector with properties:  
  
Collection properties:  
  Geometry: 'line'  
  Metadata: [1x1 struct]  
Vertex properties:  
  (2 features concatenated with 1 delimiter)  
  X: [1 2 3 NaN 4 5 6]  
  Y: [0 0 0 NaN 1 1 1]  
  Z: [41 42 43 NaN 56 50 59]  
Feature properties:  
  Name: {'Feature 1' 'Feature 2'}  
  ID: [1 2]
```

Construct a Mapshape Vector Containing Multiple Features and Indexing Behaviors

Load the data and create x, y, and z arrays. Create a level list to use to bin the z values.

```
seamount = load('seamount');  
x = seamount.x; y = seamount.y; z = seamount.z;  
  
levels = [unique(floor(seamount.z/1000)) * 1000; 0];
```

Construct a mapshape object and assign the X and Y Vertex properties to the binned x and y values. Create a new Z Vertex property to contain the binned z values. Add a Levels Feature property to contain the lowest level value per feature.

```
shape = mapshape;  
for k = 1:length(levels) - 1  
  index = z >= levels(k) & z < levels(k+1);  
  shape(k).X = x(index);  
  shape(k).Y = y(index);  
  shape(k).Z = z(index);  
  shape(k).Level = levels(k);  
end
```

Add a Color Feature property to denote a color for that feature, and specify that the geometry is 'point'


```
shape.Color = {'red', 'green', 'blue', 'cyan', 'black'};
shape.Geometry = 'point'
```

```
shape =
```

```
5x1 mapshape vector with properties:
```

```
Collection properties:
```

```
Geometry: 'point'
```

```
Metadata: [1x1 struct]
```

```
Vertex properties:
```

```
(5 features concatenated with 4 delimiters)
```

```
X: [1x298 double]
```

```
Y: [1x298 double]
```

```
Z: [1x298 double]
```

```
Feature properties:
```

```
Level: [-5000 -4000 -3000 -2000 -1000]
```

```
Color: {'red' 'green' 'blue' 'cyan' 'black'}
```

Add metadata information. `Metadata` is a scalar structure containing information for the entire set of properties. Any type of data may be added to the structure.

```
shape.Metadata.Caption = seamount.caption;
shape.Metadata
```

```
ans =
```


```
Caption: [1x229 char]
```

Display the point data in 2-D.

```
figure
```


```
for k=1:length(shape)
    mapshow(shape(k).X, shape(k).Y, ...
        'MarkerEdgeColor', shape(k).Color, ...
        'Marker', 'o', ...
        'DisplayType', shape.Geometry)
end
```

```
legend(num2str(shape.Level'))
```



Display data as a 3-D scatter plot.

```
figure  
scatter3(shape.X, shape.Y, shape.Z)
```



Construct a Mapshape Vector and Add Metadata and Indexing

This example shows how to use selective indexing behavior of a mapshape vector, and how to add a Metadata property.

Construct a mapshape vector from a structure array

```
filename = 'concord_roads.shp';  
S = shaperead(filename);  
shape = mapshape(S)
```

```
shape =
```

```
609x1 mapshape vector with properties:

Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
Vertex properties:
    (609 features concatenated with 608 delimiters)
    X: [1x5422 double]
    Y: [1x5422 double]
Feature properties:
    STREETNAME: {1x609 cell}
    RT_NUMBER: {1x609 cell}
    CLASS: [1x609 double]
    ADMIN_TYPE: [1x609 double]
    LENGTH: [1x609 double]
```

Add a `Filename` field to the `Metadata` structure and then construct a new mapshape object with only CLASS 4 (major road) designation.

```
shape.Metadata.Filename = filename;
class4 = shape(shape.CLASS == 4)
```

```
class4 =
```

```
26x1 mapshape vector with properties:

Collection properties:
    Geometry: 'line'
    Metadata: [1x1 struct]
Vertex properties:
    (26 features concatenated with 25 delimiters)
    X: [1x171 double]
    Y: [1x171 double]
Feature properties:
    STREETNAME: {1x26 cell}
    RT_NUMBER: {1x26 cell}
    CLASS: [4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4 4]
    ADMIN_TYPE: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
    LENGTH: [1x26 double]
```

Construct a Mapshape Vector and Sort the Dynamic Properties

This example show how features can be sorted by using the indexing behavior of the mapshape class.

You can create a new mapshape vector that contains a subset of dynamic properties by adding the name of a property or a cell array of property names to the last index in the () operator.

Read data from file directly in mapshape constructor.

```
shape = mapshape(shaperead('tsunamis'))
shape =
    162x1 mapshape vector with properties:
    Collection properties:
        Geometry: 'point'
        Metadata: [1x1 struct]
    Vertex properties:
        (162 features concatenated with 161 delimiters)
            X: [1x323 double]
            Y: [1x323 double]
    Feature properties:
        Cause: {1x162 cell}
        Cause_Code: [1x162 double]
        Country: {1x162 cell}
        Day: [1x162 double]
        Desc_Deaths: [1x162 double]
        Eq_Mag: [1x162 double]
        Hour: [1x162 double]
        Iida_Mag: [1x162 double]
        Intensity: [1x162 double]
        Location: {1x162 cell}
        Max_Height: [1x162 double]
        Minute: [1x162 double]
        Month: [1x162 double]
        Num_Deaths: [1x162 double]
        Second: [1x162 double]
        Val_Code: [1x162 double]
        Validity: {1x162 cell}
        Year: [1x162 double]
```

Alphabetize the Feature properties.

```
shape = shape(:, sort(fieldnames(shape)))  
shape =  
162x1 mapshape vector with properties:  
Collection properties:  
    Geometry: 'point'  
    Metadata: [1x1 struct]  
Vertex properties:  
(162 features concatenated with 161 delimiters)  
    X: [1x323 double]  
    Y: [1x323 double]  
Feature properties:  
    Cause: {1x162 cell}  
    Cause_Code: [1x162 double]  
    Country: {1x162 cell}  
    Day: [1x162 double]  
    Desc_Deaths: [1x162 double]  
    Eq_Mag: [1x162 double]  
    Hour: [1x162 double]  
    Iida_Mag: [1x162 double]  
    Intensity: [1x162 double]  
    Location: {1x162 cell}  
    Max_Height: [1x162 double]  
    Minute: [1x162 double]  
    Month: [1x162 double]  
    Num_Deaths: [1x162 double]  
    Second: [1x162 double]  
    Val_Code: [1x162 double]  
    Validity: {1x162 cell}  
    Year: [1x162 double]
```

Modify the mapshape vector to contain only the specified dynamic properties.

```
shape = shape(:, {'Year', 'Month', 'Day', 'Hour', 'Minute'})  
shape =  
162x1 mapshape vector with properties:  
Collection properties:  
    Geometry: 'point'  
    Metadata: [1x1 struct]  
Vertex properties:
```

```
(162 features concatenated with 161 delimiters)
    X: [1x323 double]
    Y: [1x323 double]
Feature properties:
    Year: [1x162 double]
    Month: [1x162 double]
    Day: [1x162 double]
    Hour: [1x162 double]
    Minute: [1x162 double]
```

Create a new mapshape vector in which each feature contains the points for the same year. Copy the data from a mappoint vector to ensure that NaN feature separators are not included. Create a subsection of data to include only Year and Country dynamic properties.

```
points = mappoint(shaperead('tsunamis'));
points = points(:, {'Year', 'Country'});
years = unique(points.Year);
multipoint = mapshape();
multipoint.Geometry = 'point';
for k = 1:length(years)
    index = points.Year == years(k);
    multipoint(k).X = points(index).X;
    multipoint(k).Y = points(index).Y;
    multipoint(k).Year = years(k);
    multipoint(k).Country = points(index).Country;
end
multipoint % Display

multipoint =
```

53x1 mapshape vector with properties:

```
Collection properties:
    Geometry: 'point'
    Metadata: [1x1 struct]
Vertex properties:
(53 features concatenated with 52 delimiters)
    X: [1x214 double]
    Y: [1x214 double]
    Country: {1x214 cell}
Feature properties:
    Year: [1x53 double]
```

Display the third from the end feature.

```
multipoint(end-3)

ans =

1x1 mapshape vector with properties:

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Vertex properties:
  X: [3.6340 -62.1800 143.9100]
  Y: [36.9640 16.7220 41.8150]
  Country: {'ALGERIA' 'MONTSERRAT' 'JAPAN'}
Feature properties:
  Year: 2003
```

Definitions

Collection Properties

Collection properties contain only one value per class instance. In contrast, the Feature and Vertex property types have attribute values associated with each feature or with each vertex in a set that defines a feature. `Geometry` and `Metadata` are the only two Collection properties.

Vertex Properties

Vertex properties provide a scalar number or a character vector for each vertex in a mapshape object. Vertex properties are suitable for attributes that vary spatially from point to point (vertex to vertex) along a line. Examples of such spatially varying attributes could be elevation, speed, temperature, or time. `X` and `Y` are Vertex properties since they contain a scalar number for each vertex in a mapshape vector.

Attribute values are associated with each vertex during construction or by using dot notation after construction. This process is similar to adding dynamic fields to a structure. Dynamic Vertex property values of an individual feature match its `X` and `Y` values in length.

Feature Properties

Feature properties provide one value (a scalar number, string scalar, or a character vector) for each feature in a mapshape vector. They are suitable for properties, such as name, owner, serial number, or age, that describe a given feature (an element of a mapshape vector) as a whole. Like Vertex properties, Feature properties can be added during construction or by using dot notation after construction.

Tips

- If X, Y, or a dynamic property is set with more values than features in the mapshape vector, then all other properties expand in size using 0 for numeric values and an empty character vector (' ') for cell values.
- If a dynamic property is set with fewer values than the number of features, then this dynamic property expands to match the size of the other properties.
- If the X or Y property of the mapshape vector is set with fewer values than contained in the object, then all other properties shrink in size.
- If either X or Y is set to [], then both coordinate properties are set to [] and all dynamic properties are removed.
- If a dynamic property is set to [], then it is removed from the object.
- The mapshape vector can be indexed like any MATLAB vector. You can access any element of the vector to obtain a specific feature. The following example demonstrates this behavior:

“Construct a Mapshape Vector Containing Multiple Features and Indexing Behaviors” on page 1-934

This example builds a mapshape vector from a structure array; adds a Metadata property and demonstrates selective indexing behavior. “Construct a Mapshape Vector and Add Metadata and Indexing” on page 1-937

“Construct a Mapshape Vector and Sort the Dynamic Properties” on page 1-938

See Also

Functions

gpxread | shaperead

Objects

geopoint | geoshape | mappoint

Introduced in R2012a

mapshow

Display map data without projection

Syntax

```
mapshow(x, y)  
mapshow(S)
```

```
mapshow(x, y, Z)  
mapshow(Z, R)
```

```
mapshow(x, y, I)  
mapshow(x, y, X, cmap)  
mapshow(I, R)  
mapshow(X, cmap, R)
```

```
mapshow(filename)
```

```
mapshow( ____, Name, Value)  
mapshow(ax, ____)  
h = mapshow( ____)
```

Description

`mapshow(x, y)` displays the coordinate vectors `x` and `y` as lines. You can optionally display the coordinate vectors as points or polygons by using the `DisplayType` name-value pair argument.

`mapshow(S)` displays the vector geographic features stored in the geographic data structure `S` as points, multipoints, lines, or polygons according to the `'Geometry'` field of `S`.

- If `S` contains `'X'` and `'Y'` fields, then these fields are used directly to plot features in map coordinates.
- If `S` contains `'Lat'` and `'Lon'` fields, then the coordinates are projected with the Plate Carrée projection and a warning is issued.

You can optionally specify symbolization rules using the `SymbolSpec` name-value pair argument.

`mapshow(x, y, Z)` displays a geolocated data grid, `Z`. You can optionally display the data as a surface, mesh, texture map, or contour by using the `DisplayType` name-value pair argument.

`mapshow(Z, R)` displays a regular data grid, `Z`, with referencing object `R`. You can optionally display the data as a surface, mesh, texture map, or contour by using the `DisplayType` name-value pair argument. If `DisplayType` is 'texturemap', then `mapshow` displays the image as a texturemap on a zero-elevation surface (by setting `ZData` values to 0).

`mapshow(x, y, I)` and

`mapshow(x, y, X, cmap)` display a geolocated image as a texture map on a zero-elevation surface. The geolocated image can be a truecolor, grayscale, or binary image, `I`, or an indexed image `X` with colormap `cmap`. `x` and `y` are geolocation arrays in map coordinates. Examples of geolocated images include a color composite from a satellite swath or an image originally referenced to a different coordinate system.

`mapshow(I, R)` and

`mapshow(X, cmap, R)` display an image georeferenced to map coordinates through the referencing object `R`. The `mapshow` function constructs an image object if the display geometry permits. Otherwise, `mapshow` displays the image as a texturemap on a zero-elevation surface (by setting `ZData` values to 0).

`mapshow(filename)` displays data from the file specified according to the type of file format.

`mapshow(____, Name, Value)` modifies the displayed map by using name-value pair arguments to set the `DisplayType` and `SymbolSpec` parameters. You can also use name-value pairs to set any MATLAB graphics properties. Parameter names can be abbreviated, and case does not matter.

`mapshow(ax, ____)` sets the parent axes to `ax`.

`h = mapshow(____)` returns a handle to a MATLAB graphics object.

Examples

Overlay Vector on Orthophoto

Overlay Boston roads on an orthophoto. Note that mapshow draws a new layer in the axes rather than replacing its contents.

Display image.

```
figure
mapshow boston.tif
axis image off manual
```



Convert Boston roads to units of survey feet and overlay on orthophoto.


```
S = shaperead('boston_roads.shp');  
surveyFeetPerMeter = unitsratio('sf','meter');  
x = surveyFeetPerMeter * [S.X];  
y = surveyFeetPerMeter * [S.Y];  
mapshow(x,y)
```



Display Vector Data Customizing Line Style

Read the vector data and display it using a dotted line.

```
roads = shaperead('boston_roads.shp');  
figure  
mapshow(roads, 'LineStyle', ':');
```




Display Vector Data Using Symbol Specification

Create a symbol specification to distinguish between different types of roads. For example, you can hide very minor roads (CLASS=6) by turning off their visibility and make major roads (CLASS=1-4) more visible by increasing their line widths. This symbol specification also uses color to distinguish between types of roads.

```
roadspec = makesymbolspec('Line',...  
    {'ADMIN_TYPE',0,'Color','cyan'}, ...  
    {'ADMIN_TYPE',3,'Color','red'},...  
    {'CLASS',6,'Visible','off'},...  
    {'CLASS',[1 4],'LineWidth',2});
```

Display the vector data using the symbol specification.

```
figure  
mapshow('boston_roads.shp','SymbolSpec',roadspec);
```




Override Default Properties of the Line

Create a symbol specification and specify the default color used for lines. As seen in the previous example, the default is blue. This example sets the default to black.

```
roadspec = makesymbolspec('Line',...  
    {'Default', 'Color', 'black'}, ...  
    {'ADMIN_TYPE',0,'Color','c'}, ...  
    {'ADMIN_TYPE',3,'Color','r'},...  
    {'CLASS',6,'Visible','off'},...  
    {'CLASS',[1 4],'LineWidth',2});
```

Display the vector data, using the symbol specification. Note how the major roads displayed in blue in the previous example are now black.

```
figure  
mapshow('boston_roads.shp','SymbolSpec',roadspec);
```



Override Symbol Specification on Command Line

Create a symbol specification, setting various properties.

```
roadspec = makesymbolspec('Line',...
    {'Default', 'Color', 'yellow'}, ...
    {'ADMIN_TYPE', 0, 'Color', 'c'}, ...
    {'ADMIN_TYPE', 3, 'Color', 'r'}, ...
    {'CLASS', 6, 'Visible', 'off'}, ...
    {'CLASS', [1 4], 'LineWidth', 2});
```

Display the vector data, specifying the color on the command line.

```
figure  
mapshow('boston_roads.shp', 'Color', 'black', 'SymbolSpec', roadspec);
```



Overlay Polygon and Lines on Orthophoto

Read orthophoto.


```
[ortho, cmap] = imread('concord_ortho_w.tif');
```

Read vector data.

```
R = worldfileread('concord_ortho_w.tfw', 'planar', size(ortho));
```


Display the orthophoto with the vector data.

```
figure  
mapshow(ortho,cmap,R)
```




Read polygon vector data representing a pond with three islands (feature 14 in the file). Note that the islands are visible in the orthophoto through three "holes" in the pond polygon.

```
pond = shaperead('concord_hydro_area.shp', 'RecordNumbers', 14);  
mapshow(pond, 'FaceColor', [0.3 0.5 1], 'EdgeColor', 'black')
```



Overlay road vector data in the same figure.

```
mapshow('concord_roads.shp', 'Color', 'red', 'LineWidth', 1);
```




Display Terrain Data as Mesh, Surface, and 3-D Surface

Read SDTS DEM terrain data for Mount Washington.

```
[Z, R] = sdtsemread('9129CATD.DDF');
```


View the terrain data as a mesh.

```
figure  
mapshow(Z, R, 'DisplayType', 'mesh');  
demcmap(Z)
```




View the terrain data as a surface.

```
figure  
mapshow(Z, R, 'DisplayType', 'surface');  
demcmap(Z)
```



View the terrain data as a 3-D surface.

```
view(3);  
axis normal
```

Display Grid and Contour Lines


Read the terrain data files for Mount Washington and Mount Dartmouth.

```
[Z_W, R_W] = arcgridread('MtWashington-ft.grd');  
[Z_D, R_D] = arcgridread('MountDartmouth-ft.grd');
```

Display the terrain data as a surface in the $z == 0$ plane, so that overlying contour lines and labels are visible.


```
figure  
hold on
```

```
mapshow(zeros(size(Z_W)),R_W, 'CData',Z_W, 'DisplayType', 'surface')
mapshow(zeros(size(Z_D)),R_D, 'CData',Z_D, 'DisplayType', 'surface')
axis equal
```




Overlay black contour lines and labels.

```
cW = mapshow(Z_W, R_W, 'DisplayType', 'contour', ...
'LineColor','black', 'ShowText', 'on');
cD = mapshow(Z_D, R_D, 'DisplayType', 'contour', ...
'LineColor','black', 'ShowText', 'on');
```



Set the colormap appropriate to terrain elevation.

```
demcmap(Z_W)
```



Input Arguments

x, y — x- or y-coordinates

numeric vector | M -by- N numeric matrix

x- or y coordinates, specified as a numeric vector or an M -by- N numeric matrix. x and y must be the same size. If x and y are matrices, they represent coordinate arrays or a geolocation array in map coordinates. x and y may contain embedded NaNs to delimit individual lines or polygon parts.

S — Geographic features

geographic data structure | dynamic vector

Geographic features, specified as a geographic data structure or dynamic vector.

Z — Data grid*M*-by-*N* array

Data grid, specified as an *M*-by-*N* array that may contain NaN values. Z is either a georeferenced data grid, or a regular data grid associated with a geographic reference R. The size of *x* and *y* must match the size of Z.

Data Types: double

R — Map reference

map raster reference object | matrix

Map reference, specified as one of the following. For more information about referencing matrices, see “Georeferenced Raster Data”.

| Type | Description |
|-----------------------------|--|
| Map raster reference object | <p>MapCellsReference or MapPostingsReference or GeographicPostingsReference map raster reference object that relates the subscripts of Z to map coordinates. The RasterSize property must be consistent with the size of the data grid, size(Z).</p> <p>If R is a MapPostingsReference object, then the 'image' and 'texturemap' values of DisplayType are not accepted.</p> |
| Matrix | <p>3-by-2 numeric matrix that transforms raster row and column indices to or from map coordinates according to:</p> $[x \ y] = [row \ col \ 1] * R$ |

I — Truecolor, grayscale, or binary image*M*-by-*N*-by-3 array | *M*-by-*N* array

Truecolor, grayscale, or binary image, specified as an *M*-by-*N*-by-3 array for truecolor images, or an *M*-by-*N* array for grayscale or binary images. *x* and *y* must be *M*-by-*N* arrays.

X — Indexed image*M*-by-*N* array

Indexed image with color map defined by `cmap`, specified as an *M*-by-*N* array. `x` and `y` must be *M*-by-*N* arrays.

cmap — Color map*c*-by-3 matrix

Color map of indexed image `X`, specified as an *c*-by-3 numeric matrix. There are *c* colors in the color map, each represented by a red, green, and blue pixel value.

filename — File name

character vector | string scalar

File name, specified as a string scalar or character vector. `mapshow` automatically sets the `DisplayType` parameter according to the format of the data.

| Format | DisplayType |
|---------------------------------|---|
| Shape file | 'point', 'multipoint', 'line', or 'polygon' |
| GeoTIFF | 'image' |
| TIFF/JPEG/PNG with a world file | 'image' |
| ARC ASCII GRID | 'surface' (can be overridden) |
| SDTS raster | 'surface' (can be overridden) |

Data Types: char | scalar

ax — Parent axes

axes object

Parent axes, specified as an axes object.

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

Example: `'DisplayType', 'point'`

DisplayType — Display type

'point' | 'multipoint' | 'line' | 'polygon' | 'image' | 'surface' | 'mesh' |
'texturemap' | 'contour'

Type of graphic display for the data, specified as the comma-separated pair consisting of 'DisplayType' and one of the following values.

| Data Format | Display Type | Type of Property |
|-------------|--------------|--------------------|
| Vector | 'point' | <i>line marker</i> |
| | 'multipoint' | <i>line marker</i> |
| | 'line' | <i>line</i> |
| | 'polygon' | <i>patch</i> |
| Image | 'image' | <i>surface</i> |
| Grid | 'surface' | <i>surface</i> |
| | 'mesh' | <i>surface</i> |
| | 'texturemap' | <i>surface</i> |
| | 'contour' | <i>contour</i> |

Valid values of DisplayType depend on the format of the map data. For example, if the map data is a geolocated image or georeferenced image, then the only valid value of DisplayType is 'image'.

Different display types support different map data class types:

| Display Type | Supported Class Types |
|--------------|-------------------------------|
| Image | |
| Surface | single and double |
| Texture map | All numeric types and logical |

SymbolSpec — Symbolization rules

structure

Symbolization rules to be used for displaying vector data, specified as a symbolSpec structure returned by makesymbolspec. When both SymbolSpec and one or more graphics properties are specified, the graphics properties will override any settings in the symbolSpec structure.

To change the default symbolization rule for a Name, Value pair in the `symbolSpec` structure, prefix the word 'Default' to the graphics property name.

Output Arguments

h — Parent axes

handle object | modified patch object

Parent axes, returned as a handle to a MATLAB graphics object or, in the case of polygons, a modified patch object. If a mapstruct or shapefile name is input, `mapshow` returns the handle to an `hggroup` object with one child per feature in the mapstruct or shapefile. In the case of a polygon mapstruct or shapefile, each child is a modified patch object; otherwise it is a line object.

Tips

- If you do not want `mapshow` to draw on top of an existing map, create a new figure or subplot before calling it.
- You can use `mapshow` to display vector data in an `axesm` figure. However, you should not subsequently change the map projection using `setm`.
- If you display a polygon, do not set 'EdgeColor' to either 'flat' or 'interp'. This combination may result in a warning.
- If `S` is a geostruct (has 'Lat' and 'Lon' fields), it may be more appropriate to use `geoshow` to display them. You can project latitude and longitude coordinate values to map coordinates by displaying with `geoshow` on a map axes.

See Also

Functions

`geoshow` | `makesymbolspec` | `mapview` | `shaperead`

Objects

`MapCellsReference` | `MapPostingsReference`

Introduced before R2006a

maptriml

Trim lines to latitude-longitude quadrangle

Syntax

```
[lat,lon] = maptriml(lat0,lon0,latlim,lonlim)
```

Description

[lat,lon] = maptriml(lat0,lon0,latlim,lonlim) returns *filtered* NaN-delimited vector map data sets from which all points lying outside the desired latitude and longitude limits have been discarded. These limits are specified by the two-element vectors latlim and lonlim, which have the form [south-limit north-limit] and [west-limit east-limit], respectively.

Examples

Following is a simple example:

```
lat0 = [1:10,9:-1:0]; lon0 = -30:-11;
[lat,lon] = maptriml(lat0,lon0,[3 7],[-29 -12]);
[lat lon]
```

```
ans =
    NaN    NaN
     3    -28
     4    -27
     5    -26
     6    -25
     7    -24
    NaN    NaN
     7    -18
     6    -17
     5    -16
     4    -15
```

```
      3  -14  
NaN   NaN
```

Notice that trimmed line segment ends have NaNs inserted at trim points.

See Also

`maptrimp` | `maptrims`

Introduced before R2006a

maptrimp

Trim polygons to latitude-longitude quadrangle

Syntax

```
[latTrimmed,lonTrimmed] = maptrimp(lat,lon,latlim,lonlim)
```

Description


[latTrimmed,lonTrimmed] = maptrimp(lat,lon,latlim,lonlim) trims the polygons in lat and lon to the quadrangle specified by latlim and lonlim. latlim and lonlim are two-element vectors, defining the latitude and longitude limits respectively. lat and lon must be vectors that represent valid polygons.

Examples

Trim Dataset to Specific Geographic Area

Read coastline data and display it on a map.

```
load coastlines  
figure  
mapshow(coastlon,coastlat,'DisplayType','polygon');
```




Trim the dataset.

```
latlim = [-50 50];  
lonlim = [-100 50];  
[latTrimmed,lonTrimmed] = maptrim(coastlat,coastlon, ...  
    latlim, lonlim);
```

Display the trimmed dataset.

```
figure  
mapshow(lonTrimmed,latTrimmed, 'DisplayType', 'polygon');
```



Tips

maptrimp conditions the longitude limits such that:

- `lonlim(2)` always exceeds `lonlim(1)`
- `lonlim(2)` never exceeds `lonlim(1)` by more than 360
- `lonlim(1) < 180` or `lonlim(2) > -180`
- Ensure that if the quadrangle span the Greenwich meridian, then that meridian appears at longitude 0.

See Also

`maptriml` | `maptrims`

Introduced before R2006a

maptrims

Trim regular data grid to latitude-longitude quadrangle

Syntax

```
[Z_trimmed] = maptrims(Z,R,latlim,lonlim)
[Z_trimmed] = maptrims(Z,R,latlim,lonlim,cellDensity)
[Z_trimmed, R_trimmed] = maptrims(...)
```

Description

`[Z_trimmed] = maptrims(Z,R,latlim,lonlim)` trims a regular data grid `Z` to the region specified by `latlim` and `lonlim`. By default, the output grid `Z_trimmed` has the same sample size as the input. `R` can be a geographic raster reference object, a referencing vector, or a referencing matrix. If `R` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z)` and its `RasterInterpretation` must be 'cells'.

If `R` is a referencing vector, it must be a 1-by-3 vector with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If `R` is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to/from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If `R` is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. `latlim` and `lonlim` are two-element vectors, defining the latitude and longitude limits, respectively. The `latlim` vector has the form:

```
[southern_limit northern_limit]
```

Likewise, the `lonlim` vector has the form:

```
[western_limit eastern_limit]
```

When an individual value in `latlim` or `lonlim` corresponds to a parallel or meridian that runs precisely along cell boundaries, the output grid will extend all the way to that limit. But if a limiting parallel or meridian cuts through a column or row of input cells, then the limit will be adjusted inward. In other words, the requested limits will be truncated as necessary to avoid partial cells.

`[Z_trimmed] = maptrims(Z,R,latlim,lonlim,cellDensity)` uses the scalar `cellDensity` to reduce the size of the output. If `R` is a referencing vector, then `R(1)` must be evenly divisible by `cellDensity`. If `R` is a referencing matrix, then the inverse of each element in the first two rows (containing "deltaLat" and "deltaLon") must be evenly divisible by `cellDensity`.

`[Z_trimmed, R_trimmed] = maptrims(...)` returns a referencing vector, matrix, or object for the trimmed data grid. If `R` is a referencing vector, then `R_trimmed` is a referencing vector. If `R` is a referencing matrix, then `R_trimmed` is a referencing matrix. If `R` is a geographic raster reference object, then `R_trimmed` is either a geographic raster reference object (when `Z_trimmed` is non-empty) or `[]` (when `Z_trimmed` is empty).

Examples

```
load topo
[subgrid,subrefvec] = maptrims(topo,topolegend,...
                               [80.25 85.3],[165.2 170.7])

subgrid =
    -2826    -2810    -2802    -2793
    -2915    -2913    -2905    -2884
    -3192    -3186    -3165    -3122
    -3399    -3324    -3273    -3214

subrefvec =
     1     85    166
```

The upper left corner of the grid might differ slightly from that of the requested region. `maptrims` uses the corner coordinates of the first cell inside the limits.

See Also

`maptriml` | `maptrimp` | `resizem`

Introduced before R2006a

mapview

Interactive map viewer

Syntax

```
mapview
```

Description

mapview opens the Map Viewer app in an empty state. Use the Map Viewer to view geospatial data in map (x - y) coordinates. The Map Viewer works with vector, image, and raster data grids in a map coordinate system. You can load data, pan and zoom on the map, control the map scale of your screen display, control the order, visibility, and symbolization of map layers, annotate your map, and click to learn more about individual vector features. mapview complements mapshow and geoshow, which are for constructing maps in ordinary figure windows in a less interactive, script-oriented way.

For usage information, see the following sections. You can also work through the Map Viewer tutorial, “Tour Boston with the Map Viewer App”.

Importing Data

The Map Viewer opens with no data loaded and an empty map display window. The first step is to import a data set. Use the options in the **File** menu to select data from a file or from the MATLAB workspace:

Import From File

Use the file browsing dialog to open a file in one of the following formats: Shapefile, GeoTIFF, SDTS DEM, Arc ASCII Grid, TIFF, JPEG, or PNG with world file. This option imports the data into the viewer but does not add it to your workspace.

To view standard-format geodata files provided with the toolbox, set your working folder or navigate the Map Viewer Open dialog to

`matlabroot/toolbox/map/mapdata`

Import From Workspace

Images. Use the **Raster Data > Image** import dialog to select a **Referencing matrix or object name** and **Raster data name** for the image from the list of workspace variables. If the image type is truecolor (RGB), specify which band represents the red, green, and blue intensities. (The `RasterInterpretation` of the referencing object must be 'cells'.)

Data grids. Use the **Raster Data > Grid** import dialog to select X and Y geolocation and data grid array names from the list of workspace variables.

Vector data. Use the **Vector Data > Map coordinates** import dialog to select X and Y variables for map coordinates from the list of workspace variables and identify the type of geometry to be displayed (**Point**, **Line**, or **Polygon**). The X and Y variables can specify multiple line segments or multiple polygons if they contain NaNs at matching locations in the coordinate vectors.

Vector geographic data structure. Use the **Vector Data > Geographic data structure** import dialog to select the struct that contains vector map data from the list of workspace variables.

Once you import your first data set, the Map Viewer automatically sets the limits of its map display window to the spatial extent of the imported data.

Working in Map Coordinates

As you move any of the Map Viewer cursors across the map display area, the coordinate readout in the lower left corners shows you the cursor position in map X and Y coordinates.

The Map Viewer requires that all currently viewed data sets possess the same coordinate system and length units. This is likely to be the case for data sets that originated from a common source. If it is not the case, you will need to adjust coordinates before importing data into the Map Viewer.

If some or all of your data is in geographic coordinates, use `proj fwd` or `mfwdtran` to project latitudes and longitudes to your desired map coordinate system before you import it. When starting from a different projection, you must first unproject to latitude and

longitude using `projinv` or `minvtran`, then reproject with `projfwd` or `mfwdtran`. You might also need to adjust the horizontal datum of your data using, for example, the free GEOTRANS (Geographic Translator) application from the Geospatial Sciences Division of the U.S. National Geospatial-Intelligence Agency (NGA). If you simply need a change of units, multiply by the appropriate conversion factor obtained from `unitsratio`.

`mapview` can also display data in unprojected geographic coordinates, if you consistently substitute longitude for map X and latitude for map Y. Geographic coordinates must be consistently expressed in either degrees or radians (not both at once). When using geographic coordinates, do not specify the viewer's map units (see below); you can only use the Map Viewer's map scale display when working in linear units of length.

Setting Map Units and Scale

If you tell the Map Viewer which length unit you are using, it can calculate an approximate map scale for your onscreen display. Set the map units with either the drop-down menu at the bottom of the display or the **Set Map Units** item in the **Tools** menu.

The scale computed by the Map Viewer is displayed in the window just above the map units drop-down. To change your display scale while keeping the center of the map display fixed, simply edit this text box.

Make sure to format your text in the standard way ($1:N$, where N is a positive number such that a distance on the ground is N times the same distance on your screen, e.g., $1:24000$).

The scale is approximate because it depends on the MATLAB estimate of the size of your screen pixels. It is also approximate if your projection introduces significant distortion. If your data falls in a fairly small area and you use a conformal projection (e.g., UTM with all data in a single zone), the scale will be very consistent across your entire map.

Navigating Your Map

By default, the Map Viewer sets the limits of your map window to match the extent of the first data set that you load. You will probably want to adjust this to see some areas in greater detail.

The Map Viewer provides several tools to control the limits of your map window and the map scale of the data display. Some are familiar from standard MATLAB figure windows.

- **Zoom in:** Drag a box to zoom in on a specific area or click a point to zoom in with that point centered in the map display.
- **Zoom out:** Click a point to zoom out with that point centered in the map display.
- **Pan tool:** Click, hold, and drag to reposition the selected point in the display window, while holding the map scale fixed. Release when you are satisfied with new display limits.
- **Fit to window:** Set the map display to enclose all currently loaded data layers. This is equivalent to selecting **Fit to Window** in the **View** menu.
- **Back to previous view:** Click this button once to return the map scale and display center to their values prior to the most recent zoom, pan, or scale change. Click repeatedly to undo earlier changes. This is equivalent to selecting **Previous View** in the **View** menu.

Another way to zoom in or out while keeping the center of the view fixed at the same map coordinates is to directly edit the map scale box at the bottom of the screen.

Managing Map Layers

Each time you import a set of vectors, an image, or a data grid into the Map Viewer, the new data is stored in a new map layer. The layers form an ordered stack. Each layer is listed as an item in the **Layers** menu, with its position in the menu indicating its position in the stack.

When you import a new layer, the Map Viewer automatically places it at the top of the layer stack. To reposition a layer in the stack, select it in the **Layers** menu, slide right, and select **To Top**, **To Bottom**, **Move Up**, or **Move Down** from the pop-up submenu.

The vector features or raster in a given layer obscure coincident elements of any underlying layers. To control layers that are obscuring one another, you can also toggle layer visibility on and off. Use the item **Visible** in the slide-right menu. Or, simply remove a layer from the Map Viewer via the **Remove** item in the slide-right menu. Remember that even if a layer's visibility is *on*, the layer does not appear if its contents are located completely outside the current display limits or are obscured by another layer.

Symbolizing Vector Features

When point, line, and polygon layers are loaded, the Map Viewer initializes their graphics properties as follows:

| Geometry | Properties |
|-------------------------|--|
| Point (line objects) | LineStyle = 'none' Marker = 'x' MarkerEdgeColor = <randomly generated value> MarkerFaceColor = 'none' |
| Line (line objects) | Color = <randomly generated value> LineStyle = '-' Marker = 'none' |
| Polygon (patch objects) | EdgeColor = [0 0 0] FaceColor = <randomly generated value> |

To override symbolism defaults for a vector layer, use `makesymbolspec` to create a symbol specification in the workspace. A `symbolspec` contains a set of rules for setting vector graphics properties based on the values of feature attributes. For instance, if you have a line layer representing roads of various classes (e.g., major highway, secondary road, etc.), you can create a `symbolspec` to use a different color, line width, or line style for each road class. See the `makesymbolspec` help for examples and to learn how to construct a `symbolspec`. If you regularly work with data sets sharing a common set of feature attributes, you might want to save one or more `symbolspecs` in a MAT-file (or save calls to `makesymbolspec` in a MATLAB program file).

Once you have a `symbolspec` in your workspace, select your vector layer in the **Layers** menu, then slide right and click **Set Symbol Spec**, which opens a dialog box. Use the dialog box to select the `symbolspec` from your workspace.

Getting Information About Vector Features

The **Datatip** tool and the **Info** tool provide different ways to check the attributes of vector features that you select graphically. Before using either tool you must designate one of your vector layers as *active*. (The default active layer is the first one that you imported.) Either use the **Active Layer** drop-down menu at the bottom of your screen or select the layer in the **Layers** menu, slide right, and select **Active**. Having a designated active layer

ensures that when you click a feature you don't inadvertently select an overlapping feature from a different layer.

- **Datatip tool:** The **Datatip** tool displays a feature attribute in a text label each time you click a vector feature. By default the attribute is the first one in the layer's attribute list. To change which attribute is used, select the layer in the **Layers** menu, slide right, and click **Set Layer Attribute**. In the dialog that follows, select a different attribute, or **Index**. If you choose **Index**, the Map Viewer displays the one-based index value corresponding to a given feature—based on its position in the input file or workspace array. To remove a text label, right-click it and choose **Delete datatip** from the context menu. Or choose **Delete all datatips** from the context menu or the **Tools** menu.
- **Info tool:** The **Info** tool opens a separate text window each time you click a vector feature. The window displays all the attribute names and values for that feature, in contrast to the **Datatip** tool, which displays only the value of a single attribute. If you need to compare two or more features, simply click each one and view the info windows together. Use its close button to close an info window when you're done with it, or choose **Close All Info Windows** from the **Tools** menu.

Annotating Your Map

Use the **text**, **line**, or **arrow** annotation tools to mark and highlight points of interest on your map, or select the corresponding items in the **Insert** menu. Note that to insert an additional object of the same type, you must reselect the appropriate tool. Use the **Select annotations** tool and **Edit** menu to modify or remove your annotations. The Map Viewer manages annotations separately from data layers; annotations always stay on top. Note that annotations cannot be saved as graphic objects, although you can export maps containing annotations to an image format as described below.

Creating and Using Additional Views

Use **New View** on the **File** menu to create an additional Map Viewer window linked to an existing window. Consider using an additional window when you want to see your map at different scales at the same time (e.g., a detailed view plus an overview), or when you want to simultaneously see different areas of the map at large scale. You can create as many additional windows as you need, and close them when you want. Your **mapview** session ends when you close the last window.

Options for creating a new viewer window include: **Duplicate Current View**, **Full Extent**, **Full Extent of Active Layer**, and **Selected Area**. Click and drag with the **Select area** tool to define a selected area.

A new viewer window differs from existing windows mainly in terms of the visible map extent and scale (it also omits annotations and any labels you added with the `datatip` tool). You will see the same layers in the same order with the same settings (including the active layer). Updates to layers (insertion/removal, order, visibility, label attribute, and symbolization) in one viewer window are propagated automatically to all the windows with which it is linked. Updates to annotations and `datatip` labels are not propagated between viewers. If you need two different layer configurations in different windows, launch a second `mapview` from the command line instead of creating an additional window. The views it contains will not be linked to previous ones.

Exporting Your Map

The Map Viewer allows you to export all or part of your map for use in a publication or on a Web page. Use **File > Save As Raster Map** to export an image of either the current display extent or an area outlined with the **Select area** tool. Select a format (PNG, TIFF, JPEG) from the drop-down menu in the export dialog. For maps including vector layers, PNG (Portable Network Graphics) is often the best choice. This format provides excellent quality, good compression, and is well supported by modern Web browsers. The export process automatically creates a world file (ending with suffix `tfw`, `jgw`, or `pgw`) as well; the pair of files constitute a georeferenced image that itself can be displayed with `mapview`, `mapshow`, and many external GIS packages.

See Also

`arcgridread` | `geoshow` | `geotiffread` | `makesymbolspec` | `mapshow` | `sdtstemread` | `shaperead` | `updategeostruct` | `worldfileread`

Introduced before R2006a

mdistort

Display contours of constant map distortion

Syntax

```
mdistort
mdistort off
mdistort parameter
mdistort(parameter,levels)
mdistort(parameter,levels,gsize)
h = mdistort(...)
```

Description

`mdistort`, with no input arguments, toggles the display of contours of projection-induced distortion on the current map axes. The magnitude of the distortion is reported in percent.

`mdistort off` removes the contours.

`mdistort parameter` displays contours of distortion for the specified parameter. Recognized parameters are:

| Parameter | Value |
|-----------------------|--|
| 'area' | |
| 'angles' | maximum angular distortion of right angles |
| 'scale' or 'maxscale' | maximum scale (the default) |
| 'minscale' | minimum scale |
| 'parscale' | scale along the parallels |
| 'merscale' | scale along the meridians |
| 'scaleratio' | ratio of maximum and minimum scale |

`mdistort(parameter, levels)` specifies the levels for which the contours are drawn. `levels` is a vector of values as used by `contour`. If empty, the default levels are used.

`mdistort(parameter, levels, gsize)` controls the size of the underlying graticule matrix used to compute the contours. `gsize` is a two-element vector containing the number of rows and columns. If omitted, the default Mapping Toolbox graticule size of `[50 100]` is assumed.

`h = mdistort(...)` returns a handle to the `contourgroup` object containing the contours and text.

Background

Map projections inevitably introduce distortions in the shape and size of objects as they are transformed from three-dimensional spherical coordinates to two-dimensional Cartesian coordinates. The amount and type of distortion vary between projections, over the projection, and with the selection of projection parameters such as standard parallels. This function provides a quantitative graphical display of distortion parameters.


`mdistort` is not intended for use with UTM. Distortion is minimal within a given UTM zone. `mdistort` issues a warning if a UTM projection is encountered.

Examples

View Extreme Area Distortion of Mercator Projection

The extreme area distortion of the Mercator projection. This makes it ill-suited for global displays.


```
figure
axesm mercator
load coastlines
frame;
plotm(coastlat,coastlon,'color',.5*[1 1 1])
mdistort('area', [1 30 100 200 500 1000])
```



View Lines of Zero Distortion for Bonne Projection

The lines of zero distortion for the Bonne projection follow the central meridian and the standard parallel.

```
figure
axesm bonne
load coastlines
framem;
plotm(coastlat,coastlon,'color',.5*[1 1 1])
mdistort('angles', 0:15:90)
parallelui
```




View Distortion of Conic Projection with Properly Chosen Parallels

An equidistant conic projection with properly chosen parallels can map the conterminous United States with less than 1.5% distortion.

```
figure
usamap conus
load conus
patchm(uslat, uslon, [1 0.7 0])
plotm(statelat, statelon)
patchm(gtlakelat, gtlakelon, 'cyan')
```

```
framem off; gridm off; mlabel off; plabel off
mdistort('parscale', -2:.5:2)
parallelui
```



Tips

`mdistort` can help in the placement of standard parallels for projections. Standard parallels are generally placed to minimize distortion over the region of interest. The default parallel locations might not be appropriate for maps of smaller regions. By using `mdistort` and `parallelui`, you can immediately see how the movement of parallels reduces distortion.

See Also

`distortcalc` | `tissot` | `vfdtran`

meanm

Mean location of geographic coordinates

Syntax

```
[latmean,lonmean] = meanm(lat,lon)
[latmean,lonmean] = meanm(lat,lon,units)
[latmean,lonmean] = meanm(lat,lon,ellipsoid)
```

Description

`[latmean,lonmean] = meanm(lat,lon)` returns row vectors of the geographic mean positions of the columns of the input latitude and longitude points.

`[latmean,lonmean] = meanm(lat,lon,units)` indicates the angular units of the data. The default angle unit is 'degrees'.

`[latmean,lonmean] = meanm(lat,lon,ellipsoid)` specifies the shape of the Earth using `ellipsoid`, which can be a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. The default ellipsoid model is a spherical Earth, which is sufficient for most applications.

If a single output argument is used, then `geomeans = [latmean,longmean]`. This is particularly useful if the original `lat` and `lon` inputs are column vectors.

Background

Finding the mean position of geographic points is more complicated than simply averaging the latitudes and longitudes. `meanm` determines mean position through three-dimensional vector addition. See “Geographic Statistics for Point Locations on a Sphere” in the *Mapping Toolbox User's Guide*.

Examples

Find Mean Position of Geographic Points

Create some random latitudes.

```
rng(0, 'twister')
lats = rand(3)

lats = 3×3

    0.8147    0.9134    0.2785
    0.9058    0.6324    0.5469
    0.1270    0.0975    0.9575
```

Create some random longitudes.

```
lons = rand(3)

lons = 3×3

    0.9649    0.9572    0.1419
    0.1576    0.4854    0.4218
    0.9706    0.8003    0.9157
```

Calculate the mean positions of the input geographic positions.

```
[latmean, lonmean] = meanm(lats, lons, 'radians');

[latmean, lonmean]

ans = 1×6

    0.6519    0.5581    0.6146    0.7587    0.7351    0.4250
```

See Also

[filterm](#) | [hista](#) | [histr](#) | [stdist](#) | [stdm](#)

meridianarc

Ellipsoidal distance along meridian

Syntax

```
s = meridianarc(phi1,phi2,ellipsoid)
```

Description

`s = meridianarc(phi1,phi2,ellipsoid)` calculates the (signed) distance `s` between latitudes `phi1` and `phi2` along a meridian on the ellipsoid defined by `ellipsoid`, which can be a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. Latitudes `phi1` and `phi2` are in radians. The distance `s` has the same units as the semimajor axis of the ellipsoid. If `phi2` is less than `phi1`, `s` is negative.

See Also

`meridianfwd`

Introduced in R2007a

meridianfwd

Reckon position along meridian

Syntax

```
phi2 = meridianfwd(phi1,s,ellipsoid)
```

Description

`phi2 = meridianfwd(phi1,s,ellipsoid)` determines the geodetic latitude `phi2` reached by starting at geodetic latitude `phi1` and traveling distance `s` north (positive `s`) or south (negative `s`) along a meridian on the specified `ellipsoid`. `ellipsoid` is a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. Latitudes `phi1` and `phi2` are in radians, and `s` has the same units as the semimajor axis of the ellipsoid.

See Also

`meridianarc`

Introduced in R2007a

meshgrat

Construct map graticule for surface object display

Syntax

```
[lat, lon] = meshgrat(Z, R)
[lat, lon] = meshgrat(Z, R, gratsize)
[lat, lon] = meshgrat(lat, lon)
[lat, lon] = meshgrat(latlim, lonlim, gratsize)
[lat, lon] = meshgrat(lat, lon, angleunits)
[lat, lon] = meshgrat(latlim, lonlim, angleunits)
[lat, lon] = meshgrat(latlim, lonlim, gratsize, angleunits)
```

Description

`[lat, lon] = meshgrat(Z, R)` constructs a graticule for use in displaying a regular data grid, `Z`. In typical usage, a latitude-longitude graticule is projected, and the grid is warped to the graticule using MATLAB graphics functions. In this two-argument calling form, the graticule size is equal to the size of `Z`. `R` can be a geographic raster reference object, a referencing vector, or a referencing matrix.

If `R` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z)`.

If `R` is a referencing vector, it must be 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If `R` is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to/from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If `R` is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel.

`[lat, lon] = meshgrat(Z, R, gratsize)` produces a graticule of size `gratsize`. `gratsize` is a two-element vector of the form `[number_of_parallels number_of_meridians]`. If `gratsize = []`, then the graticule returned has the default size 50-by-100. (But if `gratsize` is omitted, a graticule of the same size as `Z` is returned.) A finer graticule uses larger arrays and takes more memory and time but produces a higher fidelity map.

`[lat, lon] = meshgrat(lat, lon)` takes the vectors `lat` and `lon` and returns graticule arrays of size `numel(lat)`-by-`numel(lon)`. In this form, `meshgrat` is similar to the MATLAB function `meshgrid`.

`[lat, lon] = meshgrat(latlim, lonlim, gratsize)` returns a graticule mesh of size `gratsize` that covers the geographic limits defined by the two-element vectors `latlim` and `lonlim`.

`[lat, lon] = meshgrat(lat, lon, angleunits)`, `[lat, lon] = meshgrat(latlim, lonlim, angleunits)`, and `[lat, lon] = meshgrat(latlim, lonlim, gratsize, angleunits)` where `angleunits` can be either `'degrees'` (the default) or `'radians'`.

The graticule mesh is a grid of points that are projected on a map axes and to which surface map objects are warped. The fineness, or resolution, of this grid determines the quality of the projection and the speed of plotting. There is no hard and fast rule for sufficient graticule resolution, but in general, cylindrical projections need very few graticules in the longitudinal direction, while complex curve-generating projections require more.

Examples

Make a (coarse) graticule for the entire world:

```
latlim = [-90 90];  
lonlim = [-180 180];  
[lat,lon] = meshgrat(latlim,lonlim,[3 6])
```

```
lat =  
-90.0000 -90.0000 -90.0000 -90.0000 -90.0000 -90.0000  
      0      0      0      0      0      0  
 90.0000  90.0000  90.0000  90.0000  90.0000  90.0000  
lon =  
-180.0000 -108.0000 -36.0000  36.0000 108.0000 180.0000
```

```
-180.0000 -108.0000 -36.0000 36.0000 108.0000 180.0000  
-180.0000 -108.0000 -36.0000 36.0000 108.0000 180.0000
```

These paired coordinates are the graticule vertices, which are projected according to the requirements of the desired map projection. Then a surface object like the `topo` map can be warped to the grid.

See Also

`meshgrid` | `meshm` | `surfacem` | `surfm`

meshlstrm

3-D lighted shaded relief of regular data grid

Syntax

```
meshlstrm(Z,R)
meshlstrm(Z,R,[azim elev])
meshlstrm(Z,R,[azim elev],cmap)
meshlstrm(Z,R,[azim elev],cmap,clim)
h = meshlstrm(...)
```

Description

`meshlstrm(Z,R)` displays the regular data grid `Z` colored according to elevation and surface slopes. `R` can be a referencing vector, a referencing matrix, or a geographic raster reference object.

If `R` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z)`.

If `R` is a referencing vector, it must be a 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If `R` is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to/from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If `R` is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. By default, shading is based on a light to the east (90 deg.) at an elevation of 45 degrees. Also by default, the colormap is constructed from 16 colors and 16 grays. Lighting is applied before the data is projected. The current axes must have a valid map projection definition.

`meshlsrc(Z,R,[azim elev])` displays the regular data grid `Z` with the light coming from the specified azimuth and elevation. Angles are specified in degrees, with the azimuth measured clockwise from North, and elevation up from the zero plane of the surface.

`meshlsrc(Z,R,[azim elev],cmap)` displays the regular data grid `Z` using the specified colormap. The number of grayscales is chosen to keep the size of the shaded colormap below 256. If the vector of `azimuth` and `elevation` is empty, the default locations are used. Color axis limits are computed from the data.


`meshlsrc(Z,R,[azim elev],cmap,clim)` uses the provided color axis limits, which by default are computed from the data.

`h = meshlsrc(...)` returns the handle to the surface drawn.

Examples

Create a new colormap using `demcmap`, with white colors for the sea and default colors for land. Use this colormap for a lighted shaded relief map of the world.

```
korea = load('korea.mat');
Z = korea.map;
R = georasterref('RasterSize', size(Z), ...
    'Latlim', [30 45], 'Lonlim', [115 135]);
worldmap(Z, R)
meshlsrc(Z, R, [45, 65])
```



Tips

This function effectively multiplies two colormaps, one with color based on elevation, the other with a grayscale based on the slope of the surface, to create a new colormap. This produces an effect similar to using a light on a surface, but with all of the visible colors actually in the colormap. Lighting calculations are performed on the unprojected data.

See Also

`meshgrat` | `meshm` | `pcolorm` | `surfacem` | `surflm` | `surflsrm`

Introduced before R2006a

meshm

Project regular data grid on map axes

Syntax

```
meshm(Z,R)
meshm(Z,R,gratsize)
meshm(Z,R,gratsize,alt)
meshm( ____,param1,val1,param2,val2,...)
H = meshm( ____)
```

Description

`meshm(Z,R)` will display the regular data grid `Z` warped to the default projection graticule. `R` can be a referencing vector, a referencing matrix, or a geographic raster reference object.

If `R` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z)`.

If `R` is a referencing vector, it must be a 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If `R` is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to/from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If `R` is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. The current axes must have a valid map projection definition.

`meshm(Z,R,gratsize)` displays a regular data grid warped to a graticule mesh defined by the 1-by-2 vector `gratsize`. `gratsize(1)` indicates the number of lines of constant latitude (parallels) in the graticule, and `gratsize(2)` indicates the number of lines of constant longitude (meridians).


`meshm(Z,R,gratsize,alt)` displays the regular surface map at the altitude specified by `alt`. If `alt` is a scalar, then the grid is drawn in the $z = \text{alt}$ plane. If `alt` is a matrix, then `size(alt)` must equal `gratsize`, and the graticule mesh is drawn at the altitudes specified by `alt`. If the default graticule is desired, set `gratsize = []`.

`meshm(___, param1, val1, param2, val2, ...)` uses optional parameter name-value pairs to control the properties of the surface object constructed by `meshm`. (If data is placed in the `UserData` property of the surface, then the projection of this object cannot be altered once displayed.)

`H = meshm(___)` returns the handle to the surface drawn.

Examples

```
korea = load('korea.mat');  
Z = korea.map;  
R = georasterref('RasterSize', size(Z), ...  
    'Latlim', [30 45], 'Lonlim', [115 135]);  
worldmap(Z, R)  
meshm(Z, R)  
demcmap(Z)
```



See Also

geoshow | mapshow | meshgrat | pcolorm | surfacem | surfm

Introduced before R2006a

mfdtran

Project geographic features to map coordinates

Syntax

```
[x,y] = mfdtran(lat,lon)
[x,y,z] = mfdtran(lat,lon,alt)
[...] = mfdtran(mstruct,...)
```

Description

`[x,y] = mfdtran(lat,lon)` applies the forward transformation defined by the map projection in the current map axes. You can use this function to convert point locations and line and polygon vertices given in latitudes and longitudes to a planar, projected map coordinate system.

`[x,y,z] = mfdtran(lat,lon,alt)` applies the forward projection to 3-D input, resulting in 3-D output. If the input `alt` is empty or omitted, then `alt = 0` is assumed.

`[...] = mfdtran(mstruct,...)` requires a valid map projection structure as the first argument. In this case, no map axes is needed.

Examples

Transform Geographic Data into Map Coordinates

Get geographic location data for District of Columbia.

```
dc = shaperead('usastatelo', 'UseGeoCoords', true,...
    'Selector',{@(name) strcmpi(name,'District of Columbia')},...
    'Name'});
lat = [dc.Lat]';
lon = [dc.Lon]';
[lat lon]
```

```
ans = 10x2

    38.9000   -77.0700
    38.9500   -77.1200
    39.0000   -77.0300
    38.9000   -76.9000
    38.7800   -77.0300
    38.8000   -77.0200
    38.8700   -77.0200
    38.9000   -77.0700
    38.9000   -77.0700
         NaN         NaN
```

Obtain the UTM zone for this point.

```
dczone = utmzone(mean(lat, 'omitnan'), mean(lon, 'omitnan'))
```

```
dczone =
'18S'
```

Set up the UTM coordinate system based on this information.

```
utmstruct = defaultm('utm');
utmstruct.zone = dczone;
utmstruct.geoid = wgs84Ellipsoid;
utmstruct = defaultm(utmstruct)

utmstruct = struct with fields:
    mapprojection: 'utm'
           zone: '18S'
    angleunits: 'degrees'
    aspect: 'normal'
    falsenorthing: 0
    falseeasting: 500000
    fixedorient: []
           geoid: [1x1 referenceEllipsoid]
    maplatlimit: [32 40]
    maplonlimit: [-78 -72]
    mapparallels: []
    nparallels: 0
           origin: [0 -75 0]
    scalefactor: 0.9996
           trimlat: [-80 84]
           trimlon: [-180 180]
```

```
        frame: 'off'
        ffill: 100
    fedgecolor: [0.1500 0.1500 0.1500]
    ffacecolor: 'none'
        flatlimit: [32 40]
    flinewidth: 2
        flonlimit: [-3 3]
        grid: 'off'
    galtitude: Inf
        gcolor: [0.1500 0.1500 0.1500]
    glinestyle: ':'
    glinewidth: 0.5000
mlineexception: []
    mlinefill: 100
    mlinelimit: []
    mlinelocation: 1
    mlinevisible: 'on'
plineexception: []
    plinefill: 100
    plinelimit: []
    plinelocation: 1
    plinevisible: 'on'
        fontangle: 'normal'
        fontcolor: [0.1500 0.1500 0.1500]
        fontname: 'Helvetica'
        fontsize: 10
        fontunits: 'points'
        fontweight: 'normal'
    labelformat: 'compass'
    labelrotation: 'off'
        labelunits: 'degrees'
    meridianlabel: 'off'
    mlabellocation: 1
    mlabelparallel: 40
    mlabelround: 0
    parallellabel: 'off'
    plabellocation: 1
    plabelmeridian: -78
    plabelround: 0
```

Project the District of Columbia data from geographic coordinates into map coordinates for UTM zone 18S.

```
[x,y] = mfdtran(utmstruct,lat,lon)
```

$x = 10 \times 1$
 $10^5 \times$

3.2049
3.1629
3.2421
3.3524
3.2367
3.2459
3.2476
3.2049
3.2049
NaN

$y = 10 \times 1$
 $10^6 \times$

4.3077
4.3134
4.3187
4.3074
4.2943
4.2965
4.3043
4.3077
4.3077
NaN

See Also

[defaultm](#) | [gcm](#) | [minvtran](#) | [projfwd](#) | [projinv](#) | [vfwddtran](#) | [vinvtran](#)

Introduced before R2006a

minaxis

Semiminor axis of ellipse

Note Support for nonscalar input, including the syntax `b = minaxis(vec)`, will be removed in a future release.

Syntax

```
b = minaxis(semimajor,e)
b = minaxis(vec)
```

Description

`b = minaxis(semimajor,e)` computes the semiminor axis of an ellipse (or ellipsoid of revolution) given the semimajor axis and eccentricity. The input data can be scalar or matrices of equal dimensions.

`b = minaxis(vec)` assumes a 2 element vector (`vec`) is supplied, where `vec = [semimajor, e]`.

See Also

`axes2ecc` | `flat2ecc` | `majaxis` | `n2ecc`

Introduced before R2006a

minvtran

Unproject features from map to geographic coordinates

Syntax

```
[lat,lon] = minvtran(x,y)
[lat,lon,alt] = minvtran(x,y,z)
[...] = minvtran(mstruct,...)
```

Description

`[lat,lon] = minvtran(x,y)` applies the inverse transformation defined by the map projection in the current map axes. Using `minvtran`, you can convert point locations and line and polygon vertices in a planar, projected map coordinate system to latitudes and longitudes.

`[lat,lon,alt] = minvtran(x,y,z)` applies the inverse projection to 3-D input, resulting in 3-D output. If the input `Z` is empty or omitted, then `Z = 0` is assumed.

`[...] = minvtran(mstruct,...)` takes a valid map projection structure as the first argument. In this case, no map axes is needed.

Examples

Before using any transformation functions, it is necessary to create a map projection structure. You can do this with `axesm` or the `defaultm` function:

```
mstruct = defaultm('mercator');
mstruct.origin = [38.89 -77.04 0];
mstruct = defaultm(mstruct);
```

The following latitude and longitude data for the District of Columbia is obtained from the `usastatelo` shapefile:

```
dc = shaperead('usastatelo', 'UseGeoCoords', true,...
    'Selector',{@(name) strcmpi(name,'District of Columbia')},...)
```

```
'Name'});  
lat = [dc.Lat]';  
lon = [dc.Lon]';  
[lat lon]  
  
ans =  
38.9000 -77.0700  
38.9500 -77.1200  
39.0000 -77.0300  
38.9000 -76.9000  
38.7800 -77.0300  
38.8000 -77.0200  
38.8700 -77.0200  
38.9000 -77.0700  
38.9000 -77.0500  
38.9000 -77.0700  
      NaN      NaN
```

This data can be projected into Cartesian coordinates of the Mercator projection using the `mfwdran` function:

```
[x,y] = mfwdran(mstruct,lat,lon);  
[x y]
```

```
ans =  
-0.0004  0.0002  
-0.0011  0.0010  
 0.0001  0.0019  
 0.0019  0.0002  
 0.0001 -0.0019  
 0.0003 -0.0016  
 0.0003 -0.0003  
-0.0004  0.0002  
-0.0001  0.0002  
-0.0004  0.0002  
      NaN      NaN
```

To transform the projected x-y data back into the unprojected geographic system, use the `minvtran` function:

```
[lat2,lon2] = minvtran(mstruct,x,y);  
[lat2 lon2]
```

```
ans =  
38.9000 -77.0700
```

```
38.9500 -77.1200
39.0000 -77.0300
38.9000 -76.9000
38.7800 -77.0300
38.8000 -77.0200
38.8700 -77.0200
38.9000 -77.0700
38.9000 -77.0500
38.9000 -77.0700
      NaN      NaN
```

See Also

[axesm](#) | [defaultm](#) | [gcm](#) | [mfwdtran](#) | [projfwd](#) | [projinv](#) | [vfwddtran](#) | [vinvtran](#)

Introduced before R2006a

mlabel

Toggle and control display of meridian labels

Syntax

```
mlabel  
mlabel('on')  
mlabel('off')  
mlabel('reset')  
mlabel(parallel)  
mlabel(MapAxesPropertyName,PropertyValue,...)
```

Description

`mlabel` toggles the visibility of meridian labeling on the current map axes.

`mlabel('on')` sets the visibility of meridian labels to 'on'.

`mlabel('off')` sets the visibility of meridian labels to 'off'.

`mlabel('reset')` resets the displayed meridian labels using the currently defined meridian label properties.

`mlabel(parallel)` sets the value of the `MLabelParallel` property of the map axes to the value of `parallel`. This determines the parallel upon which the labels are placed (see `axesm`). The options for `parallel` are a scalar latitude or 'north', 'south', or 'equator'.

`mlabel(MapAxesPropertyName,PropertyValue,...)` allows paired map axes' property names and property values to be passed in. For a complete description of map axes properties, see the `axesm` reference page in this guide.

Meridian label handles can be returned in `h` if desired.

See Also

axesm | mlabelzero22pi | plabel | setm

Introduced before R2006a

mlabelzero22pi

Convert meridian labels to 0-360 degree range

Syntax


mlabelzero22pi

Description


mlabelzero22pi displays longitude labels in the range of 0 to 360 degrees east of the prime meridian.

Examples

```
% create a map
figure('color','w'); axesm('miller','grid','on'); tightmap;
mlabel on; plabel on
```



```
% Display longitude labels in the range of 0 to 360 degrees  
mlabelzero22pi
```



See Also

`mlabel`

Introduced before R2006a

n2ecc

Eccentricity of ellipse from third flattening

Note Support for nonscalar input, including the special two-column syntax described below, will be removed in a future release.

Syntax

Description

$\text{ecc} = \text{n2ecc}(n)$ computes the eccentricity of an ellipse (or ellipsoid of revolution) given the parameter n (the "third flattening"). n is defined as $(a-b)/(a+b)$, where a is the semimajor axis and b is the semiminor axis. Except when the input has 2 columns (or is a row vector), each element is assumed to be a third flattening and the output ecc has the same size as n .

$\text{ecc} = \text{n2ecc}(n)$, where n has two columns (or is a row vector), assumes that the second column is a third flattening, and a column vector is returned.

See Also

[axes2ecc](#) | [ecc2n](#)

namem

Names of graphics objects

Syntax

```
obj_names = namem  
obj_names = namem(h)
```

Description

`obj_names = namem` returns the names of all the objects on the current axes. The name of an object is the value of its `Tag` property, if specified. Otherwise, the name of the object is the value of its `Type` property. The values of these properties are either set at object creation or defined using the `tagm` function.


`obj_names = namem(h)` returns the name of the object (or objects) specified by the array, `h`.

Examples

Get List of Graphics Objects in Map Display

Display a map in a figure window.

```
load korea  
h = worldmap(map, refvec);  
set(h, 'Visible', 'off')  
geoshow(h, map, refvec, 'DisplayType', 'texturemap')  
demcmap(map)
```



Get a list of all the names of graphics objects in the figure.

```
obj_names = namem
```

```
obj_names = 6x8 char array  
  'PLabel '  
  'MLabel '  
  'Parallel'  
  'Meridian'  
  'surface '  
  'Frame  '
```

Convert the array of names into a cell array of character vectors.

```
obj_names_cell = cellstr(obj_names)
```

```
obj_names_cell = 6x1 cell array
    {'PLabel' }
    {'MLabel' }
    {'Parallel'}
    {'Meridian'}
    {'surface' }
    {'Frame'  }
```

Input Arguments

h — Graphics objects

array

Graphics objects, specified as an array.

Output Arguments

obj_names — Names of graphics objects

character array

Names of graphics objects, returned as a character array. `namem` removes duplicate object names from the array.

Note: Use `cellstr(obj_names)` to convert `obj_names` to a cell array of character vectors.

See Also

`clma` | `clmo` | `handlem` | `hidem` | `showm` | `tagm`

Introduced before R2006a

nanclip

Clip vector data with NaNs at specified pen-down locations

Syntax

```
dataout = nanclip(datain)
dataout = nanclip(datain,pendowncmd)
```

Description

`dataout = nanclip(datain)` and `dataout = nanclip(datain,pendowncmd)` return the pen-down delimited data in the matrix `datain` as NaN-delimited data in `dataout`. When the first column of `datain` equals `pendowncmd`, a segment is started and a NaN is inserted in all columns of `dataout`. The default `pendowncmd` is -1.

Pen-down delimited data is a matrix with a first column consisting of pen commands. At the beginning of each segment in the data, this first column has an entry corresponding to a pen-down command. Other entries indicate that the segment is continuing. NaN-delimited data consists of columns of data, each segment of which ends in a NaN in every data column. Since there is no pen command column, the NaN-delimited format can represent the same data in one fewer columns; the remaining columns have more entries, one for each NaN (that is, for each segment).

Examples

```
datain = [-1 45 67; 0 23 54; 0 28 97; -1 47 89; 0 56 12]
```

```
datain =
    -1    45    67           % Begin first segment
     0    23    54
     0    28    97
    -1    47    89           % Begin second segment
     0    56    12
```

```
dataout = nanclip(datain)
```

```
dataout =  
    45    67  
    23    54  
    28    97  
   NaN   NaN           % End first segment  
    47    89  
    56    12  
   NaN   NaN           % End second segment
```

See Also

spcread

Introduced before R2006a

nanm

Construct regular data grid of NaNs

Note `nanm` is not recommended and may be removed in a future release. Instead, use `georefcells` to construct a geographic raster reference object and then use `nan` to initialize a data grid of the appropriate size:

```
R = georefcells(latlim,lonlim,1/scale,1/scale);  
Z = nan(R.RasterSize);
```

Syntax

```
[Z,refvec] = nanm(latlim,lonlim,scale)
```

Description

`[Z,refvec] = nanm(latlim,lonlim,scale)` returns a regular data grid consisting entirely of NaNs and a three-element referencing vector for the returned Z. The two-element vectors `latlim` and `lonlim` define the latitude and longitude limits of the geographic region. They should be of the form `[south north]` and `[west east]`, respectively. The scalar `scale` specifies the number of rows and columns per degree of latitude and longitude.

Examples

```
[Z,refvec] = nanm([46,51],[-79,-75],1)
```

```
Z =  
NaN NaN NaN NaN  
NaN NaN NaN NaN  
NaN NaN NaN NaN  
NaN NaN NaN NaN  
NaN NaN NaN NaN
```

refvec =
1 51 -79

See Also

limitm | onem | sizem | spzerom | zerom

Introduced before R2006a

navfix

Mercator-based navigational fix

Syntax

```
[latfix,lonfix] = navfix(lat,long,az)
[latfix,lonfix] = navfix(lat,long,range,casetype)
[latfix,lonfix] = navfix(lat,long,az_range,casetype)
[latfix,lonfix] = navfix(lat,long,az_range,casetype,drlat,drlon)
```

Description

`[latfix,lonfix] = navfix(lat,long,az)` returns the intersection points of rhumb lines drawn parallel to the observed bearings, `az`, of the landmarks located at the points `lat` and `long` and passing through these points. One bearing is required for each landmark. Each possible pairing of the n landmarks generates one intersection, so the total number of resulting intersection points is the combinatorial $n \text{ choose } 2$. The calculation time therefore grows rapidly with n .

`[latfix,lonfix] = navfix(lat,long,range,casetype)` returns the intersection points of Mercator projection circles with radii defined by `range`, centered on the landmarks located at the points `lat` and `long`. One range value is required for each landmark. Each possible pairing of the n landmarks generates up to two intersections (circles can intersect twice), so the total number of resulting intersection points is the combinatorial $2 \text{ times } (n \text{ choose } 2)$. The calculation time therefore grows rapidly with n . In this case, the variable `casetype` is a vector of 0s the same size as the variable `range`.

`[latfix,lonfix] = navfix(lat,long,az_range,casetype)` combines ranges and bearings. For each element of `casetype` equal to 1, the corresponding element of `az_range` represents an azimuth to the associated landmark. Where `casetype` is a 0, `az_range` is a range.

`[latfix,lonfix] = navfix(lat,long,az_range,casetype,drlat,drlon)` returns for each possible pairing of landmarks only the intersection that lies closest to the dead reckoning position indicated by `drlat` and `drlon`. When this syntax is used, all

included landmarks' bearing lines or range arcs must intersect. If any possible pairing fails, the warning `No Fix` is displayed.

Background

This is a navigational function. It assumes that all latitudes and longitudes are in degrees and all distances are in nautical miles. In navigation, piloting is the practice of fixing one's position based on the observed bearing and ranges *to* fixed landmarks (points of land, lighthouses, smokestacks, etc.) *from* the navigator's vessel. In conformance with navigational practice, bearings are treated as rhumb lines and ranges are treated as the radii of circles on a Mercator projection.

In practice, at least three azimuths (bearings) and/or ranges are required for a usable fix. The resulting intersections are unlikely to coincide exactly. Refer to “Navigation” in the *Mapping Toolbox User's Guide* for a more complete description of the use of this function.

Examples


For a fully illustrated example of the application of this function, refer to the “Navigation” section in the *Mapping Toolbox User's Guide*.

Imagine you have two landmarks, at (15°N,30.4°W) and (14.8°N,30.1°W). You have a visual bearing to the first of 280° and to the second of 160°. Additionally, you have a range to the second of 12 nm. Find the intersection points:

```
[latfix,lonfix] = navfix([15 14.8 14.8],[-30.4 -30.1 -30.1],...  
                        [280 160 12],[1 1 0])
```

```
latfix =  
    14.9591      NaN  
    14.9680    14.9208  
    14.9879      NaN  
lonfix =  
   -30.1599      NaN  
   -30.2121   -29.9352  
   -30.1708      NaN
```

Here is an illustration of the geometry:



Limitations

Traditional plotting and the `navfix` function are limited to relatively short distances. Visual bearings are in fact great circle azimuths, not rhumb lines, and range arcs are actually arcs of small circles, not of the planar circles plotted on the chart. However, the mechanical ease of the process and the practical limits of visual bearing ranges and navigational radar ranges (~30 nm) make this limitation moot in practice. The error contributed because of these assumptions is minuscule at that scale.

Tips

The outputs of this function are matrices providing the locations of the intersections for all possible pairings of the n entered lines of bearing and range arcs. These matrices therefore have $n\text{-choose-}2$ rows. In order to allow for two intersections per combination, these matrices have two columns. Whenever there are fewer than two intersections for that combination, one or two NaNs are returned in that row.

When a dead reckoning position is included, these matrices are column vectors.

See Also

crossfix | dreckon | gcwaypts | gcxgc | gcxsc | legs | polyxpoly | rhxrh | scxsc | track

Introduced before R2006a

ned2aer

Local Cartesian NED to local spherical AER

Syntax

```
[az,elev,slantRange] = ned2aer(xNorth,yEast,zDown)
[ ___ ] = ned2aer( ___ ,angleUnit)
```

Description

[az,elev,slantRange] = ned2aer(xNorth,yEast,zDown) returns coordinates in a local spherical system corresponding to coordinates xNorth, yEast, zDown in a local north-east-down (NED) Cartesian system having the same local origin. Any of the three numerical input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

[___] = ned2aer(___ ,angleUnit) adds angleUnit which specifies the units outputs az, elev.

Input Arguments

xNorth — Local NED x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the local NED system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: single | double

yEast — Local NED y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the local NED system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: single | double

zDown — Local NED z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the local NED system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: `single` | `double`

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: `char` | `string`

Output Arguments

az — Azimuth angles

scalar value | vector | matrix | N-D array

Azimuth angles in the local spherical system, returned as a scalar value, vector, matrix, or N-D array. Azimuths are measured clockwise from north. Units are determined by the input argument `angleUnit`, if supplied; values are in degrees, otherwise. When in degrees, they lie in the half-open interval [0 360).

elev — Elevation angles

scalar value | vector | matrix | N-D array

Elevation angles in the local spherical system, returned as a scalar value, vector, matrix, or N-D array. Elevations are with respect to a plane perpendicular to the spheroid surface normal. Units determined by the input argument `angleUnit`, if supplied; values are in degrees, otherwise. When in degrees, they lie in the closed interval [-90 90].

slantRange — Distances from local origin

scalar value | vector | matrix | N-D array

Distances from origin in the local spherical system, returned as a scalar, vector, matrix, or N-D array. The straight-line, 3-D Cartesian distance is computed.

See Also

aer2ned | enu2aer

Introduced in R2012b

ned2ecef

Local Cartesian NED to geocentric ECEF

Syntax

```
[X,Y,Z] = ned2ecef(xNorth,yEast,zDown,lat0,lon0,h0,spheroid)  
[ ___ ] = ned2ecef( ___ ,angleUnit)
```

Description

[X,Y,Z] = ned2ecef(xNorth,yEast,zDown,lat0,lon0,h0,spheroid) returns Earth-Centered Earth-Fixed (ECEF) spheroid-centric Cartesian coordinates corresponding to coordinates xNorth, yEast, zDown in a local north-east-down (NED) Cartesian system. Any of the first six numeric input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

[___] = ned2ecef(___ ,angleUnit) adds angleUnit which specifies the units of inputs lat0 and lon0.

Input Arguments

xNorth — Local NED x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the local NED system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the LengthUnit property of the spheroid input.

Data Types: single | double

yEast — Local NED y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the local NED system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the `spheroid` input.

Data Types: `single` | `double`

zDown — Local NED z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the local NED system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the `spheroid` input.

Data Types: `single` | `double`

lat0 — Geodetic latitude of local origin

scalar value | vector | matrix | N-D array

Geodetic latitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lat0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon0 — Longitude of local origin

scalar value | vector | matrix | N-D array

Longitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lon0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

h0 — Ellipsoidal height of local origin

scalar value | vector | matrix | N-D array

Ellipsoidal height of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `h0` is scalar, but it need not be. (It may refer to a moving platform, for example). Units are determined by the `LengthUnit` property of the `spheroid` input.

Data Types: `single` | `double`

spheroid — Reference spheroid

`referenceEllipsoid` | `oblateSpheroid` | `referenceSphere`

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. To create a spheroid object, use the creation function specific to the object, or the `wgs84Ellipsoid` function.

Example: `spheroid = referenceEllipsoid('GRS 80');`

angleUnit — Units of angles

`'degrees'` (default) | `'radians'`

Units of angles, specified as `'degrees'` (default), or `'radians'`.

Data Types: `char` | `string`

Output Arguments

X — ECEF x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid object.

Y — ECEF y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid object.

Z — ECEF z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the spheroid object.

See Also

aer2ecef | ecef2ned | enu2ecef | ned2geodetic

Introduced in R2012b

ned2ecefv

Rotate vector from local NED to geocentric ECEF

Syntax

```
[U,V,W] = ned2ecefv(uNorth,vEast,wDown,lat0,lon0)
[ ___ ] = ned2ecefv( ___ ,angleUnit)
```

Description

`[U,V,W] = ned2ecefv(uNorth,vEast,wDown,lat0,lon0)` returns Cartesian 3-vector components in an Earth-Centered Earth-Fixed (ECEF) spheroid-centric Cartesian system corresponding to the 3-vector with components `uNorth`, `vEast`, `wDown` in a local north-east-down (NED) system. Any of the five numerical input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

`[___] = ned2ecefv(___ ,angleUnit)` adds `angleUnit` which specifies the units of inputs `lat0` and `lon0`.

Input Arguments

uNorth — Vector x-components in NED system

scalar value | vector | matrix | N-D array

x-components of one or more Cartesian vectors in the local NED system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: `single` | `double`

vEast — Vector y-components in NED system

scalar value | vector | matrix | N-D array

y-components of one or more Cartesian vectors in the local ENU system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: `single` | `double`

wDown — Vector z-components in NED system

scalar value | vector | matrix | N-D array

z-components of one or more Cartesian vectors in the local NED system, specified as a scalar value, vector, matrix, or N-D array.

Data Types: `single` | `double`

lat0 — Geodetic latitude of local origin

scalar value | vector | matrix | N-D array

Geodetic latitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lat0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon0 — Longitude of local origin

scalar value | vector | matrix | N-D array

Longitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lon0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

angleUnit — Units of angles

'degrees' (default) | 'radians'

Units of angles, specified as 'degrees' (default), or 'radians'.

Data Types: `char` | `string`

Output Arguments

U — Vector x-components in ECEF system

scalar value | vector | matrix | N-D array

x-components of one or more Cartesian vectors in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array.

V — Vector y-components in ECEF system

scalar value | vector | matrix | N-D array

y-components of one or more Cartesian vectors in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array.

W — Vector z-components in ECEF system

scalar value | vector | matrix | N-D array

z-components of one or more Cartesian vectors in the spheroid-centric ECEF system, returned as a scalar value, vector, matrix, or N-D array.

See Also

`ecef2ned` | `enu2ecefv` | `ned2ecef`

Introduced in R2012b

ned2geodetic

Local Cartesian NED to geodetic

Syntax

```
[lat,lon,h] = ned2geodetic(xNorth,yEast,zDown,lat0,lon0,h0,spheroid)  
[ ___ ] = ned2geodetic( ___,angleUnit)
```

Description

[lat,lon,h] = ned2geodetic(xNorth,yEast,zDown,lat0,lon0,h0,spheroid)) returns geodetic coordinates corresponding to coordinates xNorth, yEast, zDown in a local north-east-down (NED) Cartesian system. Any of the first six numeric input arguments can be scalar, even when the others are nonscalar; but all nonscalar numeric arguments must match in size.

[___] = ned2geodetic(___,angleUnit) adds angleUnit which specifies the units of inputs lat0, lon0, and outputs lat, lon.

Input Arguments

xNorth — Local NED x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the local NED system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the LengthUnit property of the spheroid input.

Data Types: single | double

yEast — Local NED y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the local NED system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the `spheroid` input.

Data Types: `single` | `double`

zDown — Local NED z-coordinates

scalar value | vector | matrix | N-D array

z-coordinates of one or more points in the local NED system, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the `LengthUnit` property of the `spheroid` input.

Data Types: `single` | `double`

lat0 — Geodetic latitude of local origin

scalar value | vector | matrix | N-D array

Geodetic latitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lat0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

lon0 — Longitude of local origin

scalar value | vector | matrix | N-D array

Longitude of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `lon0` is scalar, but it need not be. (It may refer to a moving platform, for example). Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

h0 — Ellipsoidal height of local origin

scalar value | vector | matrix | N-D array

Ellipsoidal height of local origin (reference) point(s), specified as a scalar value, vector, matrix, or N-D array. In many cases there is one origin (reference) point, and the value of `h0` is scalar, but it need not be. (It may refer to a moving platform, for example). Units are determined by the `LengthUnit` property of the `spheroid` input.

Data Types: `single` | `double`

spheroid — Reference spheroid

`referenceEllipsoid` | `oblateSpheroid` | `referenceSphere`

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. To create a spheroid object, use the creation function specific to the object, or the `wgs84Ellipsoid` function.

Example: `spheroid = referenceEllipsoid('GRS 80');`

angleUnit — Units of angles

`'degrees'` (default) | `'radians'`

Units of angles, specified as `'degrees'` (default), or `'radians'`.

Data Types: `char` | `string`

Output Arguments

lat — Geodetic latitudes

scalar value | vector | matrix | N-D array

Geodetic latitudes of one or more points, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the input argument `angleUnit`, if supplied; values are in degrees, otherwise. When in degrees, they lie in the closed interval `[-90 90]`.

lon — Longitudes

scalar value | vector | matrix | N-D array

Longitudes of one or more points, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the input argument `angleUnit`, if supplied; values are in degrees, otherwise. When in degrees, they lie in the interval `[-180 180]`.

h — Ellipsoidal heights

scalar value | vector | matrix | N-D array

Ellipsoidal heights of one or more points, returned as a scalar value, vector, matrix, or N-D array. Units are determined by the `LengthUnit` property of the `spheroid` object

See Also

aer2geodetic | enu2geodetic | geodetic2ned | ned2ecef

Introduced in R2012b

neworig

Orient regular data grid to oblique aspect

Syntax

```
[Z,lat,lon] = neworig(Z0,R,origin)
[Z,lat,lon] = neworig(Z0,R,origin, 'forward')
[Z,lat,lon] = neworig(Z0,R,origin, 'inverse')
```

Description

`[Z,lat,lon] = neworig(Z0,R,origin)` and `[Z,lat,lon] = neworig(Z0,R,origin, 'forward')` will transform regular data grid `Z0` into an oblique aspect, while preserving the matrix storage format. In other words, the oblique map origin is not necessarily at (0,0) in the Greenwich coordinate frame. This allows operations to be performed on the matrix representing the oblique map. For example, azimuthal calculations for a point in a data grid become row and column operations if the data grid is transformed so that the north pole of the oblique map represents the desired point on the globe.

`R` can be a geographic raster reference object, a referencing vector, or a referencing matrix. If `R` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z)`.

If `R` is a referencing vector, it must be a 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If `R` is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to or from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If `R` is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. Nearest-neighbor interpolation is used by default. NaN is returned for points

outside the grid limits or for which `lat` or `lon` contain NaN. All angles are in units of degrees.

`[Z,lat,lon] = neworig(Z0,R,origin,'inverse')` transforms the regular data grid from the oblique frame to the Greenwich coordinate frame.

The `neworig` function transforms a regular data grid into a new matrix in an altered coordinate system. An analytical use of the new matrix can be realized in conjunction with the `newpole` function. If a selected point is made the *north pole* of the new system, then when a new matrix is created with `neworig`, each row of the new matrix is a constant distance from the selected point, and each column is a constant azimuth from that point.


Limitations

`neworig` only supports data grids that cover the entire globe.

Examples

This is the topo map transformed to put Sri Lanka at the North Pole:

```
load topo
origin = newpole(7,80)
origin =
    83.0000 -100.0000      0
[Z,lat,lon] = neworig(topo,topolegend,origin);
axesm miller
latlim = [ -90  90];
lonlim = [-180 180];
gratsize = [90 180];
[lat,lon] = meshgrat(latlim,lonlim,gratsize);
surfm(lat,lon,Z)
demcmap(topo)
tightmap
```



See Also

`org2pol` | `rotatem` | `setpostn`

Introduced before R2006a

newpole

Origin vector to place specific point at pole

Syntax

```
origin = newpole(polelat,polelon)
origin = newpole(polelat,polelon,units)
```

Description

`origin = newpole(polelat,polelon)` provides the `origin` vector for a transformed coordinate system based upon moving the point (`polelat`, `polelon`) to become the north pole singularity in the new system. The origin is a three-element vector of the form [`latitude longitude orientation`], where the latitude and longitude are the coordinates the new center (`origin`) had in the untransformed system, and the orientation is the azimuth of the true North Pole from the new origin point. For the `newpole` calculation, this orientation is constrained to be always 0° .

`origin = newpole(polelat,polelon,units)` specifies the units of the inputs and output, where `units` is any valid angle unit. The default is 'degrees'.

When developing transverse or oblique projections, you need transformed coordinate systems. One way to define these systems is to establish the point in the original (untransformed) system that will become the new (transformed) *north pole*.

Examples

Take a point and make it the new North Pole:

```
origin = newpole(60,180)

origin =
    30.0000      0      0
```

This makes sense: as a point 30° beyond the true North Pole on the original origin's meridian is pulled up to become the *pole*, the point originally 30° above the origin is pulled down into the origin spot.

See Also

neworig | org2pol | putpole

nm2deg

Convert spherical distance from nautical miles to degrees

Syntax

```
deg = nm2deg(nm)
deg = nm2deg(nm, radius)
deg = nm2deg(nm, sphere)
```

Description

`deg = nm2deg(nm)` converts distances from nautical miles to degrees, as measured along a great circle on a sphere with a radius of 3440.065 nm, the mean radius of the Earth.

`deg = nm2deg(nm, radius)` converts distances from nautical miles to degrees, as measured along a great circle on a sphere having the specified radius.

`deg = nm2deg(nm, sphere)` converts distances from nautical miles to degrees, as measured along a great circle on a sphere approximating an object in the Solar System.

Input Arguments

nm — Distance in nautical miles

numeric array

Distance in nautical miles, specified as a numeric array.

Data Types: `single` | `double`

radius — Radius

3440.065 (default) | numeric scalar

Radius of sphere in units of nautical miles, specified as a numeric scalar.

sphere — Sphere

'sun' | 'moon' | 'mercury' | 'venus' | 'earth' | ...

Sphere approximating an object in the Solar System, specified as one of the following values: 'sun', 'moon', 'mercury', 'venus', 'earth', 'mars', 'jupiter', 'saturn', 'uranus', 'neptune', or 'pluto'. The value of sphere is case-insensitive.

Output Arguments

deg — Distance in degrees

numeric array

Distance in degrees, returned as a numeric array.

Data Types: single | double

See Also

deg2nm | deg2rad | km2deg | nm2rad | rad2deg | sm2deg

Introduced in R2007a

nm2km

Convert nautical miles to kilometers

Syntax

`km = nm2km(nm)`

Description

`km = nm2km(nm)` converts distances from nautical miles to kilometers.

Examples

How fast is 30 knots (nautical miles per hour) in kph?

```
km = nm2km(30)
```

```
km =  
  55.5600
```

See Also

[deg2km](#) | [deg2nm](#) | [deg2sm](#) | [deg2sm](#) | [km2deg](#) | [km2rad](#) | [nm2deg](#) | [nm2rad](#) | [rad2km](#) | [rad2nm](#) | [rad2sm](#) | [sm2deg](#) | [sm2rad](#)

Introduced in R2007a

nm2rad

Convert spherical distance from nautical miles to radians

Syntax

```
rad = nm2rad(nm)
rad = nm2rad(nm, radius)
rad = nm2rad(nm, sphere)
```

Description

`rad = nm2rad(nm)` converts distances from nautical miles to radians, as measured along a great circle on a sphere with a radius of 3440.065 nm, the mean radius of the Earth.

`rad = nm2rad(nm, radius)` converts distances from nautical miles to radians, as measured along a great circle on a sphere having the specified radius.

`rad = nm2rad(nm, sphere)` converts distances from nautical miles to radians, as measured along a great circle on a sphere approximating an object in the Solar System.

Input Arguments

nm — Distance in nautical miles

numeric array

Distance in nautical miles, specified as a numeric array.

Data Types: `single` | `double`

radius — Radius

3440.065 (default) | numeric scalar

Radius of sphere in units of nautical miles, specified as a numeric scalar.

sphere — Sphere

'sun' | 'moon' | 'mercury' | 'venus' | 'earth' | ...

Sphere approximating an object in the Solar System, specified as one of the following values: 'sun', 'moon', 'mercury', 'venus', 'earth', 'mars', 'jupiter', 'saturn', 'uranus', 'neptune', or 'pluto'. The value of sphere is case-insensitive.

Output Arguments

rad — Distance in radians

numeric array

Distance in radians, returned as a numeric array.

Data Types: single | double

See Also

deg2rad | km2rad | nm2deg | rad2deg | rad2nm | sm2rad

Introduced in R2007a

nm2sm

Convert nautical to statute miles

Syntax

```
sm = nm2sm(nm)
```

Description

`sm = nm2sm(nm)` converts distances from nautical miles to statute miles.

See Also

`deg2km` | `deg2nm` | `deg2sm` | `deg2sm` | `km2deg` | `km2rad` | `nm2deg` | `nm2rad` | `rad2km` | `rad2nm` | `rad2sm` | `sm2deg` | `sm2rad`

Introduced in R2007a

northarrow

Add graphic element pointing to geographic North Pole

Syntax

```
northarrow  
northarrow('property',value,...)
```

Description

northarrow creates a default north arrow.

northarrow('property',value,...) creates a north arrow using the specified property/value pairs. Valid entries for properties are 'latitude', 'longitude', 'facecolor', 'edgecolor', 'linewidth', and 'scaleratio'. The 'latitude' and 'longitude' properties specify the location of the north arrow. The 'facecolor', 'edgecolor', and 'linewidth' properties control the appearance of the north arrow. The 'scaleratio' property represents the size of the north arrow as a fraction of the size of the axes. A 'scaleratio' value of 0.10 creates a north arrow one-tenth (1/10) the size of the axes. You can change the appearance ('facecolor', 'edgecolor', and 'linewidth') of the north arrow using the set command.


northarrow creates a north arrow symbol at the map origin on the displayed map. You can reposition the north arrow symbol by clicking and dragging its icon. Alternate clicking the icon creates an input dialog box that you can also use to change the location of the north arrow.

Modifying some of the properties of the north arrow results in replacement of the original object. Use HANDLEM('NorthArrow') to get the handles associated with the north arrow.


Examples


Create a map of the South Pole and then add the north arrow in the upper left of the map.

```
Antarctica = shaperead('landareas', 'UseGeoCoords', true, ...  
    'Selector',{@(name) strcmpi(name,{'Antarctica'})}, 'Name');  
figure;  
worldmap('south pole')  
geoshow(Antarctica,'FaceColor',[.9 .9 .9])  
northarrow('latitude', -57, 'longitude', 135);
```




Right-click the north arrow icon to activate the input dialog box. Increase the size of the north arrow symbol by changing the 'ScaleRatio' property.






Create a map of Texas and add the north arrow in the lower left of the map.

```
figure; usamap('texas')
states = shaperead('usastatelo.shp','UseGeoCoords',true);
faceColors = makesymbolspec('Polygon',...
    {'INDEX', [1 numel(states)], 'FaceColor', ...
    polcmap(numel(states))});
geoshow(states, 'DisplayType', 'polygon', ...
    'SymbolSpec', faceColors)
northarrow('latitude',25,'longitude',-105,'linewidth',1.5);
```

Change the 'FaceColor' and 'EdgeColor' properties of the north arrow.

```
h = handle('NorthArrow');  
set(h,'FaceColor',[1.000 0.8431 0.0000],...  
    'EdgeColor',[0.0100 0.0100 0.9000])
```



Limitations

You can draw multiple north arrows on the map. However, the callbacks will only work with the most recently created north arrow. In addition, since it can be displayed outside the map frame limits, the north arrow is not converted into a “mapped” object. Hence, the location and orientation of the north arrow have to be updated manually if the map origin or projection changes.

See Also

scaleruler

Introduced before R2006a

npi2pi

Wrap longitudes to [-180 180] degree interval

Note The `npi2pi` function has been replaced by `wrapTo180` and `wrapToPi`.

Syntax

```
anglout = npi2pi(anglin)
anglout = npi2pi(anglin,units)
anglout = npi2pi(anglin,units,method)
```

Description

`anglout = npi2pi(anglin)` wraps the input angle `anglin` (typically representing a longitude) to lie on the range -180 to 180 (e.g., 270° is renamed -90°).

`anglout = npi2pi(anglin,units)` specifies the angle units with any valid angle units character vector `units`. The default is 'degrees'.

`anglout = npi2pi(anglin,units,method)` allows special alternative computations to be used when `npi2pi` is called from within certain Mapping Toolbox functions. `method` can be one of the following:

- 'exact', for exact wrapping (the default value)
- 'inward', where angles are scaled by a factor of $(1 - \text{epsm}('radians'))$ before wrapping
- 'outward', where angles are scaled by a factor of $(1 + \text{epsm}('radians'))$ before wrapping

Examples

```
npi2pi(315)
```

```
ans =  
-45
```

```
npi2pi(181)
```

```
ans =  
-179
```

See Also

[wrapTo180](#) | [wrapToPi](#)

Introduced before R2006a

oblateSpheroid

Oblate ellipsoid of revolution

Description

An `oblateSpheroid` object encapsulates the interrelated intrinsic properties of an oblate ellipsoid of revolution. An oblate spheroid is symmetric about its polar axis and flattened at the poles, and includes the perfect sphere as a special case.

Creation

You can create an `oblateSpheroid` object, `s`, by entering:

```
s = oblateSpheroid;
```

on the command line.

Properties

SemimajorAxis — Equatorial radius of spheroid

1 (default) | positive, finite scalar

Equatorial radius of spheroid, specified as a positive, finite scalar. The value of `SemimajorAxis` is expressed in meters.

When the `SemimajorAxis` property is changed, the `SemiminorAxis` property scales as needed to preserve the shape of the spheroid and the values of shape-related properties including `InverseFlattening` and `Eccentricity`. The only way to change the `SemimajorAxis` property is to set it directly, using dot notation.

Example: 6378137

Data Types: double

SemiminorAxis — Distance from center of spheroid to pole

1 (default) | nonnegative, finite scalar

Distance from center of spheroid to pole, specified as a nonnegative, finite scalar. The value of `SemiminorAxis` is always less than or equal to `SemimajorAxis`, and is expressed in meters.

When the `SemiminorAxis` property is changed, the `SemimajorAxis` property remains unchanged, but the shape of the spheroid changes, which is reflected in changes in the values of `InverseFlattening`, `Eccentricity`, and other shape-related properties.

Example: 6356752

Data Types: `double`

InverseFlattening — Reciprocal of flattening

`Inf` (default) | positive scalar in the range `[1, Inf]`

Reciprocal of flattening, specified as positive scalar in the range `[1, Inf]`.

The value of inverse flattening, $1/f$, is calculated using `SemimajorAxis` value a and `SemiminorAxis` value b according to $1/f = a/(a-b)$. A value $1/f$ of `Inf` designates a perfect sphere. As $1/f$ approaches 1, the reference spheroid approaches a flattened disk.

When the `InverseFlattening` property is changed, other shape-related properties update, including `Eccentricity`. The `SemimajorAxis` property remains unchanged, but the value of `SemiminorAxis` adjusts to reflect the new shape.

Example: 300

Data Types: `double`

Eccentricity — First eccentricity of spheroid

0 (default) | nonnegative scalar in the range `[0, 1]`

First eccentricity of the spheroid, specified as nonnegative scalar in the range `[0, 1]`.

The value of eccentricity, ecc , is calculated using `SemimajorAxis` value a and `SemiminorAxis` value b according to $ecc = \sqrt{(a^2 - b^2)}/a$. A value ecc of 0 designates a perfect sphere.

When the `Eccentricity` property is changed, other shape-related properties update, including `InverseFlattening`. The `SemimajorAxis` property remains unchanged, but the value of `SemiminorAxis` adjusts to reflect the new shape.

Example: 0.08

Data Types: `double`

Flattening — Flattening of spheroid

nonnegative scalar in the range [0, 1]

This property is read-only.

Flattening of the spheroid, specified as nonnegative scalar in the range [0, 1].

The value of flattening, f , is calculated using SemimajorAxis value a and SemiminorAxis value b according to $f = (a-b)/a$.

Data Types: double

ThirdFlattening — Third flattening of spheroid

nonnegative scalar in the range [0, 1]

This property is read-only.

Third flattening of the spheroid, specified as nonnegative scalar in the range [0, 1].

The value of the third flattening, n , is calculated using SemimajorAxis value a and SemiminorAxis value b according to $n = (a-b)/(a+b)$.

Data Types: double

MeanRadius — Mean radius of the spheroid

positive, finite scalar

This property is read-only.

Mean radius of the spheroid, specified as positive, finite scalar. The MeanRadius property is expressed in meters.

The mean radius of the spheroid, r , is calculated using SemimajorAxis value a and SemiminorAxis value b according to $r = (2a+b)/3$.

Data Types: double

SurfaceArea — Surface area of the spheroid

positive, finite scalar

This property is read-only.

Surface area of the spheroid, specified as positive, finite scalar. The SurfaceArea property is expressed in square meters.

Data Types: double

Volume — Volume of the spheroid

positive, finite scalar

This property is read-only.

Volume of the spheroid, specified as positive, finite scalar. The `Volume` property is expressed in cubic meters.

Data Types: double

Examples

Create GRS 80 Ellipsoid

Create a GRS 80 ellipsoid using the `oblateSpheroid` class.

Start with a unit sphere by default.

```
s = oblateSpheroid
```

```
s =
```

`oblateSpheroid` with defining properties:

```
    SemimajorAxis: 1  
    SemiminorAxis: 1  
    InverseFlattening: Inf  
    Eccentricity: 0
```

and additional properties:

```
    Flattening  
    ThirdFlattening  
    MeanRadius  
    SurfaceArea  
    Volume
```

Reset the semimajor axis to match the equatorial radius of the GRS 80 reference ellipsoid.

```
s.SemimajorAxis = 6378137
```


s =

oblateSpheroid with defining properties:

```
SemimajorAxis: 6378137
SemiminorAxis: 6378137
InverseFlattening: Inf
Eccentricity: 0
```

and additional properties:

```
Flattening
ThirdFlattening
MeanRadius
SurfaceArea
Volume
```

The result is a sphere with radius 6,378,137 meters.

Reset the inverse flattening to the standard value for GRS 80, resulting in an oblate spheroid with a semiminor axis consistent with the value, 6,356,752.3141, tabulated in DMA Technical Memorandum 8358.1, "Datums, Ellipsoids, Grids, and Grid Reference Systems."

```
s.InverseFlattening = 298.257222101
```

s =

oblateSpheroid with defining properties:

```
SemimajorAxis: 6378137
SemiminorAxis: 6356752.31414036
InverseFlattening: 298.257222101
Eccentricity: 0.0818191910428158
```

and additional properties:

```
Flattening
ThirdFlattening
MeanRadius
```

SurfaceArea
Volume

Tips

- When you define a spheroid in terms of semimajor and semiminor axes (rather than semimajor axis and inverse flattening, or semimajor axis and eccentricity), a small loss of precision in the last few digits of `Flattening`, `Eccentricity`, and `ThirdFlattening` may occur. This is unavoidable, but does not affect the results of practical computation.

See Also

`referenceEllipsoid` | `referenceSphere` | `validateLengthUnit`

Introduced in R2012a

onem

Construct regular data grid of 1s

Note `onem` is not recommended and may be removed in a future release. Instead, use `georefcells` to construct a geographic raster reference object and then use `ones` to initialize a data grid of the appropriate size:

```
R = georefcells(latlim,lonlim,1/scale,1/scale);  
Z = ones(R.RasterSize);
```

Syntax

```
[Z,refvec] = onem(latlim,lonlim,scale)
```

Description

`[Z,refvec] = onem(latlim,lonlim,scale)` returns a regular data grid consisting entirely of 1s and a three-element referencing vector for the returned data grid, `Z`. The two-element vectors `latlim` and `lonlim` define the latitude and longitude limits of the geographic region. They should be of the form `[south north]` and `[west east]`, respectively. The scalar `scale` specifies the number of rows and columns per degree of latitude and longitude.

Examples

```
[Z,refvec] = onem([46,51],[-79,-75],1)
```

```
Z =  
    1     1     1     1  
    1     1     1     1  
    1     1     1     1  
    1     1     1     1  
    1     1     1     1
```

refvec =
1 51 -79

See Also

limitm | nanm | sizem | spzerom | zerom

Introduced before R2006a

org2pol

Location of north pole in rotated map

Syntax

```
pole = org2pol(origin)
pole = org2pol(origin,units)
```

Description

`pole = org2pol(origin)` returns the location of the North Pole in terms of the coordinate system after transformation based on the input `origin`. The `origin` is a three-element vector of the form `[latitude longitude orientation]`, where `latitude` and `longitude` are the coordinates that the new center (`origin`) had in the untransformed system, and `orientation` is the azimuth of the true North Pole from the new origin point in the transformed system. The output `pole` is a three-element vector of the form `[latitude longitude meridian]`, which gives the latitude and longitude point in terms of the original untransformed system of the new location of the true North Pole. The meridian is the longitude from the original system upon which the new system is centered.

`pole = org2pol(origin,units)` allows the specification of the angular units of the `origin` vector, where `units` is any valid angle unit. The default is 'degrees'.

When developing transverse or oblique projections, transformed coordinate systems are required. One way to define these systems is to establish the point at which, in terms of the original (untransformed) system, the (transformed) true North Pole will lie.

Examples

Perhaps you want to make (30°N,0°) the new origin. Where does the North Pole end up in terms of the original coordinate system?

```
pole = org2pol([30 0 0])
```

```
pole =  
  60.0000      0      0
```

This makes sense: pull a point 30° down to the origin, and the North Pole is pulled down 30° . A little less obvious example is the following:

```
pole = org2pol([5 40 30])
```

```
pole =  
  59.6245  80.0750  40.0000
```

See Also

[neworig](#) | [putpole](#)

outlinegeoquad

Polygon outlining geographic quadrangle

Syntax

```
[lat,lon] = outlinegeoquad(latlim,lonlim,dlat,dlon)
```

Description

`[lat,lon] = outlinegeoquad(latlim,lonlim,dlat,dlon)` constructs a polygon that traces the outline of the geographic quadrangle defined by `latlim` and `lonlim`. Such a polygon can be useful for displaying the quadrangle graphically, especially on a projection where the meridians and/or parallels do not project to straight lines. `latlim` is a two-element vector of the form: `[southern-limit northern-limit]` and `lonlim` is a two-element vector of the form: `[western-limit eastern-limit]`. `dlat` is a positive scalar that specifies a minimum vertex spacing in degrees to be applied along the meridians that bound the eastern and western edges of the quadrangle. Likewise, `dlon` is a positive scalar that specifies a minimum vertex spacing in degrees of longitude to be applied along the parallels that bound the northern and southern edges of the quadrangle. The outputs `lat` and `lon` contain the vertices of a simple closed polygon with clockwise vertex ordering.


Examples

Display the outlines of three geographic quadrangles having very different qualities on top of a simple base map:

```
figure('Color','white')
axesm('ortho','Origin',[-45 110],'frame','on','grid','on')
axis off
load coastlines
geoshow(coastlat, coastlon)

% Quadrangle covering Australia and vicinity
[lat, lon] = outlinegeoquad([-45 5],[110 175],5,5);
```

```
geoshow(lat,lon,'DisplayType','polygon','FaceAlpha',0.5);  
  
% Quadrangle covering Antarctic region  
antarcticCircleLat = dms2degrees([-66 33 39]);  
[lat, lon] = outlinegeoquad([-90 antarcticCircleLat], ...  
    [-180 180],5,5);  
geoshow(lat,lon,'DisplayType','polygon', ...  
    'FaceColor','cyan','FaceAlpha',0.5);  
  
% Quadrangle covering nominal time zone 9 hours ahead of UTC  
[lat, lon] = outlinegeoquad([-90 90], 135 + [-7.5 7.5], 5, 5);  
geoshow(lat,lon,'DisplayType','polygon', ...  
    'FaceColor','green','FaceAlpha',0.5);
```



Tips

All input and output angles are in units of degrees. Choose a reasonably small value for `dlat` (a few degrees, perhaps) when using a projection with curved meridians or curved parallels.

To avoid interpolating extra vertices along meridians or parallels, set `dlat` or `dlon` to a value of `Inf`.

Special Cases

The insertion of additional vertices is suppressed at the poles (that is, if `latlim(1) == -90` or `latlim(2) == 90`. If `lonlim` corresponds to a quadrangle width of exactly 360 degrees (`lonlim == [-180 180]`, for example), then it covers a full latitudinal zone and includes two separate, NaN-separated parts, unless either

- `latlim(1) == -90` or `latlim(2) == 90`, so that only one part is needed—a polygon that follows a parallel clockwise around one of the poles.
- `latlim(1) == -90` and `latlim(2) == 90`, so that the quadrangle encompasses the entire planet. In this case, the quadrangle cannot be represented by a latitude-longitude polygon, and an error results.

See Also

`ingeoquad` | `intersectgeoquad`

Introduced in R2008a

paperscale

Set figure properties for printing at specified map scale

Syntax

```
paperscale(paperdist,punits,surfdist,sunits)  
paperscale(paperdist,punits,surfdist,sunits,lat,long)  
paperscale(paperdist,punits,surfdist,sunits,lat,long,az)  
paperscale(paperdist,punits,surfdist,sunits,lat,long,az,gunits)  
paperscale(paperdist,punits,surfdist,sunits,lat,long,az,gunits,  
radius)  
paperscale(scale,...)  
[paperXdim,paperYdim] = paperscale(...)
```

Description

`paperscale(paperdist,punits,surfdist,sunits)` sets the figure paper position to print the map in the current axes at the desired scale. The scale is described by the geographic distance that corresponds to a paper distance. For example, a scale of 1 inch = 10 kilometers is specified as `degrees(1, 'inch', 10, 'km')`. See below for an alternate method of specifying the map scale. The surface distance units *sunits* can be any unit recognized by `unitsratio`. The paper units *punits* can be any dimensional units recognized for the figure `PaperUnits` property.

`paperscale(paperdist,punits,surfdist,sunits,lat,long)` sets the paper position so that the scale is correct at the specified geographic location. If omitted, the default is the center of the map limits.

`paperscale(paperdist,punits,surfdist,sunits,lat,long,az)` also specifies the direction along which the scale is correct. If omitted, 90 degrees (east) is assumed.

`paperscale(paperdist,punits,surfdist,sunits,lat,long,az,gunits)` also specifies the units in which the geographic position and direction are given. If omitted, 'degrees' is assumed.

`paperscale(paperdist,punits,surfdist,sunits,lat,long,az,gunits,`

radius) uses the last input to determine the radius of the sphere. `radius` can be one of the values supported by `km2deg`, or it can be the (numerical) radius of the desired sphere in units. If omitted, the default radius of the Earth is used..

`paperscale(scale, ...)`, where the numeric `scale` replaces the two property/value pairs, specifies the scale as a ratio between distance on the sphere and on paper. This is commonly notated on maps as 1:scale (e.g. 1:100 000, or 1:1 000 000). For example, `paperscale(100000)` or `paperscale(100000, lat, long)`.

`[paperXdim, paperYdim] = paperscale(...)` returns the computed paper dimensions. The dimensions are in the paper units specified. For the scale calling form, the returned dimensions are in centimeters.

Background

Maps are usually printed at a size that allows an easy comparison of distances measured on paper to distances on the Earth. The relationship of geographic distance and paper distance is termed *scale*. It is usually expressed as a ratio, such as 1 to 100,000 or 1:100,000 or 1 cm = 1 km.

Examples

The small circle measures 10 cm across when printed.

```
axesm mercator
[lat,lon] = scircle1(0,0,km2deg(5));
plotm(lat,lon)
[x,y] = paperscale(1,'centimeter',1,'km'); [x y]
```

```
ans =
    13.154    12.509
```

```
set(gca,'pos', [ 0 0 1 1])
[x,y] = paperscale(1,'centimeter',1,'km'); [x y]
```

```
ans =
    10.195    10.195
```

Limitations

The relationship between the paper and geographic coordinates holds only as long as there are no changes to the display that affect the axes limits or the relationship between geographic coordinates and projected coordinates. Changes of this type include the ellipsoid or scale factor properties of the map axes, or adding elements to the display that cause MATLAB to modify the axes autoscaling. To be sure that the scale is correct, execute `paperscale` just before printing.

See Also

`axesscale` | `daspectm` | `printpreview`

Introduced before R2006a

parametricLatitude

Convert geodetic to parametric latitude

Syntax

```
beta = parametricLatitude(phi,F)
beta = parametricLatitude(phi,F,angleUnit)
```

Description

`beta = parametricLatitude(phi,F)` returns the parametric latitude corresponding to geodetic latitude `phi` on an ellipsoid with flattening `F`.

`beta = parametricLatitude(phi,F,angleUnit)` specifies the units of input `phi` and output `beta`.

Examples

Convert Geodetic Latitude to Parametric Latitude

Create a reference ellipsoid and then convert the geodetic latitude to parametric latitude. The reference ellipsoid contains a flattening factor.

```
s = wgs84Ellipsoid;
parametricLatitude(45, s.Flattening)

ans =

    44.9038
```

Convert Geodetic Latitude Expressed in Radians to Parametric Latitude

Create a reference ellipsoid and then convert a parametric latitude expressed in radians to geodetic latitude. The reference ellipsoid contains a flattening factor.

```
s = wgs84Ellipsoid;  
parametricLatitude(pi/3, s.Flattening, 'radians')  
ans =  
    1.0457
```

Input Arguments

phi — Geodetic latitude of one or more points

scalar value, vector, matrix, or N-D array

Geodetic latitude of one or more points, specified as a scalar value, vector, matrix, or N-D array. Values must be in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

Data Types: `single` | `double`

F — Flattening of reference spheroid

scalar

Flattening of reference spheroid, specified as a scalar value.

Data Types: `single` | `double`

angleUnit — Unit of measurement for angle

'degrees' (default) | 'radians'

Unit of measurement for angle, specified as 'degrees' or 'radians'.

Data Types: `char` | `string`

Output Arguments

beta — Parametric latitudes of one or more points

scalar value, vector, matrix, or N-D array

Parametric latitudes of one or more points, returned as a scalar value, vector, matrix, or N-D array. Values are in units that match the input argument `angleUnit`, if supplied, and in degrees, otherwise.

See Also

Functions

`geocentricLatitude` | `geodeticLatitudeFromParametric`

Objects

`AuthalicLatitudeConverter` | `ConformalLatitudeConverter` |
`IsometricLatitudeConverter` | `RectifyingLatitudeConverter`

Introduced in R2013a

patchesm

Project patches on map axes as individual objects

Syntax

```
patchesm(lat, lon, cdata)
patchesm(lat, lon, z, cdata)
patchesm(..., 'PropertyName', PropertyValue, ...)
h = patchesm(...)
```

Description

`patchesm(lat, lon, cdata)` projects 2-D patch objects onto the current map axes. The input latitude and longitude data must be in the same units as specified in the current map axes. The input `cdata` defines the patch face color. If the input vectors are `NaN` clipped, then multiple patches are drawn each with a single face. Unlike `fillm` and `fill3m`, `patchesm` will always add the patches to the current map regardless of the current hold state.

`patchesm(lat, lon, z, cdata)` projects 3-D planar patches at the uniform elevation given by scalar `z`.

`patchesm(..., 'PropertyName', PropertyValue, ...)` uses the patch properties supplied to display the patch. Except for `xdata`, `ydata`, and `zdata`, all patch properties available through `patch` are supported by `patchesm`.


`h = patchesm(...)` returns the handles to the patch objects drawn.

Examples

Plot Distinct Patch Objects on Current Map Axes

Plot coastline data as distinct patch objects.


```
load coastlines
axesm sinusoid;
framem
h = patchesm(coastlat,coastlon,'b');
```



```
% Number of objects created.
length(h)

ans = 241
```

Tips

Differences between `patchesm` and `patchm`

The `patchesm` function is very similar to the `patchm` function. The significant difference is that in `patchesm`, separate patches (delineated by NaNs in the inputs `lat` and `lon`) are separated and plotted as distinct patch objects on the current map axes. The advantage to this is that less memory is required. The disadvantage is that multifaced objects cannot be treated as a single object. For example, the archipelago of the Philippines cannot be treated and handled as a single Handle Graphics® object.

When Patches Are Completely Trimmed Away

Removing graphic objects that fall outside the map frame is called trimming. If, after trimming no polygons remain to be seen within it, `patchesm` creates no patches and returns an empty 1-by-0 list of handles. When this occurs, automatic reprojection of the patch data (by changing the projection or any of its parameters) is not possible. In cases where some polygons are completely trimmed away but not others, handles returned for the trimmed polygons will be empty. No polygons or rings that have been totally trimmed away can be reprojected; to plot them again, you will need to call `patchesm` again with the original data.

See Also

`fill3m` | `fillm` | `geoshow` | `patchm`

Introduced before R2006a

patchm

Project patch objects on map axes

Syntax

```
h = patchm(lat,lon,cdata)
h = patchm(lat,lon,cdata,PropertyName,PropertyValue,...)
h = patchm(lat,lon,PropertyName,PropertyValue,...)
h = patchm(lat,lon,z,cdata)
h = patchm(lat,lon,z,cdata, PropertyName,PropertyValue,...)
```

Description

`h = patchm(lat,lon,cdata)` and `h = patchm(lat,lon,cdata,PropertyName,PropertyValue,...)` project and display patch (polygon) objects defined by their vertices given in `lat` and `lon` on the current map axes. `lat` and `lon` must be vectors. The color data, `cdata`, can be any color data designation supported by the standard MATLAB `patch` function. The object handle or handles, `h`, can be returned.

`h = patchm(lat,lon,PropertyName,PropertyValue,...)` allows any property name/property value pair supported by `patch` to be assigned to the `patchm` object. Except for `XData`, `YData`, and `ZData`, all line properties and styles available through `patch` are supported by `patchm`.


`h = patchm(lat,lon,z,cdata)` and `h = patchm(lat,lon,z,cdata,PropertyName,PropertyValue,...)` allow the assignment of an altitude, `z`, to each patch object. The default altitude is `z = 0`.

Examples

Project Patch Object on Map Axes

Project coastline data as single patch object on map axes.

```
load coastlines
axesm sinusoid;
framem
h = patchm(coastlat,coastlon,'b');
```



```
length(h)
ans = 1
```

Tips

How patchm Works

This Mapping Toolbox function is very similar to the standard MATLAB `patch` function. Like its analog, and unlike higher level functions such as `fillm` and `fill3m`, `patchm` adds patch objects to the current map axes regardless of hold state.

When A Patch Is Completely Trimmed Away

Removing graphic objects that fall outside the map frame is called trimming. If, after trimming to the map frame no polygons remain to be seen within it, `patchm` creates no patches and returns an empty 0-by-1 handle. When this occurs, automatic reprojection of the patch data (by changing the projection or any of its parameters) will not be possible. Instead, after changing the projection, call `patchm` again.

See Also

`fill3m` | `fillm` | `patchesm`

Introduced before R2006a

pcolorm

Project regular data grid on map axes in $z = 0$ plane

Syntax

```
pcolorm(lat,lon,Z)
pcolorm(latlim,lonlim,Z)
pcolorm(...,prop1,val1,prop2,val2,...)
h = pcolorm(...)
```

Description

`pcolorm(lat,lon,Z)` constructs a surface to represent the data grid `Z` in the current map axes. The surface lies flat in the horizontal plane with its `CData` property set to `Z`. `lat` and `lon` are vectors or 2-D arrays that define the latitude-longitude graticule mesh on which `Z` is displayed. For a complete description of the various forms that `lat` and `lon` can take, see `surfm`. If the hold state is 'off', `pcolorm` clears the current map.

`pcolorm(latlim,lonlim,Z)` defines the graticule using the latitude and longitude limits `latlim` and `lonlim`. These limits should match the geographic extent of `Z`, the data grid. `latlim` is a two-element vector of the form:

```
[southern_limit northern_limit]
```

Likewise, `lonlim` has the form:

```
[western_limit eastern_limit]
```

A latitude-longitude graticule of size 50-by-100 is constructed. The surface `FaceColor` property is 'texturemap', except when `Z` is precisely 50-by-100, in which case it is 'flat'.


`pcolorm(...,prop1,val1,prop2,val2,...)` applies additional MATLAB graphics properties to the surface via property/value pairs. Any property accepted by the surface may be specified, except for `XData`, `YData`, and `ZData`.

`h = pcolorm(...)` returns a handle to the surface object.

Examples

Construct a surface to represent the data grid topo.

```
figure('Color','white')
load topo
axesm miller
axis off; framem on; gridm on;
[lat lon] = meshgrat(topo,topolegend,[90 180]);
pcolorm(lat,lon,topo)
demcmap(topo)
tightmap
```



Tips

This function warps a data grid to a graticule mesh, which is projected according to the map axes property `MapProjection`. The fineness, or resolution, of this grid determines the quality of the projection and the speed of plotting it. There is no hard and fast rule for sufficient graticule resolution, but in general, cylindrical projections need fewer graticule points in the longitudinal direction than do complex curve-generating projections.

See Also

geoshow | meshgrat | meshm | surfacem | surfm

Introduced before R2006a

pix2latlon

Convert pixel coordinates to latitude-longitude coordinates

Syntax

```
[lat, lon] = pix2latlon(R, row, col)
```

Description

`[lat, lon] = pix2latlon(R, row, col)` calculates latitude-longitude coordinates `lat`, `lon` from pixel coordinates `row`, `col`. `R` is either a 3-by-2 referencing matrix that transforms intrinsic pixel coordinates to geographic coordinates, or a geographic raster reference object. `row` and `col` are vectors or arrays of matching size. The outputs `lat` and `lon` have the same size as `row` and `col`.

Examples

Find the latitude and longitude of the upper left outer corner of a 2-by-2 degree gridded data set.

```
R = makerefmat(1, 89, 2, 2);  
[UL_lat, UL_lon] = pix2latlon(R, .5, .5)
```

The output appears as follows:

```
UL_lat =  
    88  
UL_lon =  
     0
```

Find the latitude and longitude of the lower right outer corner of a 2-by-2 degree gridded data set.

```
[LR_lat, LR_lon] = pix2latlon(R, 90.5, 180.5)
```

The output appears as follows:

```
LR_lat =  
  268  
LR_lon =  
  360
```

See Also

latlon2pix | makerefmat | pix2map

Introduced before R2006a

pix2map

Convert pixel coordinates to map coordinates

Syntax

```
[x,y] = pix2map(R,row,col)
s = pix2map(R,row,col)
[...] = pix2map(R,p)
```

Description

`[x,y] = pix2map(R,row,col)` calculates map coordinates x, y from pixel coordinates row, col . R is either a 3-by-2 referencing matrix defining a two-dimensional affine transformation from intrinsic pixel coordinates to map coordinates, or a map raster reference object. row and col are vectors or arrays of matching size. The outputs x and y have the same size as row and col .

`s = pix2map(R,row,col)` combines x and y into a single array s . If row and col are column vectors of length n , then s is an n -by-2 matrix and each row ($s(k,:)$) specifies the map coordinates of a single point. Otherwise, s has size $[size(row) 2]$, and $s(k1,k2,\dots,kn,:)$ contains the map coordinates of a single point.

`[...] = pix2map(R,p)` combines row and col into a single array p . If row and col are column vectors of length n , then p should be an n -by-2 matrix such that each row ($p(k,:)$) specifies the pixel coordinates of a single point. Otherwise, p should have size $[size(row) 2]$, and $p(k1,k2,\dots,kn,:)$ should contain the pixel coordinates of a single point.

Examples

```
% Find the map coordinates for the pixel at (100,50).
R = worldfileread('concord_ortho_w.tfw');
[x,y] = pix2map(R,100,50);
```

See Also

`makerefmat` | `map2pix` | `pix2latlon` | `worldfileread`

Introduced before R2006a

pixcenters

Compute pixel centers for georeferenced image or data grid

Syntax

```
[x,y] = pixcenters(R,height,width)
[x,y] = pixcenters(r,sizea)
[x,y] = pixcenters(..., 'makegrid')
```

Description

`[x,y] = pixcenters(R,height,width)` returns the spatial coordinates of a spatially-referenced image or regular gridded data set. `R` is either a 3-by-2 referencing matrix defining a 2-dimensional affine transformation from intrinsic pixel coordinates to map coordinates, or a `MapCellsReference` object. `height` and `width` are the image dimensions. If `r` does not include a rotation (i.e., $r(1,1) = r(2,2) = \theta$), then `x` is a 1-by-`width` vector and `y` is a 1-by-`height` vector. In this case, the spatial coordinates of the pixel in row `row` and column `col` are given by `x(col)`, `y(row)`. Otherwise, `x` and `y` are each a `height`-by-`width` matrix such that `x(col,row)`, `y(col,row)` are the coordinates of the pixel with subscripts (`row,col`).

`[x,y] = pixcenters(r,sizea)` accepts the size vector `sizea = [height, width, ...]` instead of `height` and `width`.

`[x,y] = pixcenters(info)` accepts a scalar struct array with the fields

| | |
|-------------|---------------------------|
| 'RefMatrix' | 3-by-2 referencing matrix |
| 'Height' | Scalar number |
| 'Width' | Scalar number |

`[x,y] = pixcenters(..., 'makegrid')` returns `x` and `y` as `height`-by-`width` matrices even if `r` is irrotational. This syntax can be helpful when you call `pixcenters` from within a function or script.

Examples

```
[Z,R] = arcgridread('MtWashington-ft.grd');  
[x,y] = pixcenters(R, size(Z));  
h = surf(x,y,Z); axis equal; demcmap(Z)  
set(h,'EdgeColor','none')  
xlabel('x (easting in meters)')  
ylabel('y (northing in meters)')  
zlabel('elevation in feet')
```

Tips

For more information on referencing matrices, see the `makerefmat` reference page.

`pixcenters` is useful for working with `surf`, `mesh`, or `surface`, and for coordinate transformations.

See Also

Functions

`arcgridread` | `makerefmat` | `mapbbox` | `mapoutline` | `mapshow` | `pix2map` | `worldfileread`

Objects

`MapCellsReference`

Introduced before R2006a

plabel

Toggle and control display of parallel labels

Syntax

```
plabel  
plabel('on')  
plabel('off')  
plabel(meridian)  
plabel(MapAxesPropertyName,PropertyValue,...)
```

Description

`plabel` toggles the visibility of parallel labeling on the current map axes.

`plabel('on')` sets the visibility of parallel labels to 'on'.

`plabel('off')` sets the visibility of parallel labels to 'off'.

`plabel('reset')` resets the displayed parallel labels using the currently defined parallel label properties.

`plabel(meridian)` sets the value of the `PLabelMeridian` property of the map axes to the value `meridian`. This determines the meridian upon which the labels are placed (see `axesm`). The options for `meridian` are a scalar longitude or 'east', 'west', or 'prime'.

`plabel(MapAxesPropertyName,PropertyValue,...)` allows paired map axes property names and property values to be passed in. For a complete description of map axes properties, see the `axesm` reference page.

Parallel label handles can be returned in `h` if desired.

See Also

`axesm` | `mlabel` | `setm`

Introduced before R2006a

plot3m

Project 3-D lines and points on map axes

Syntax

```
h = plot3m(lat,lon,z)
h = plot3m(lat,lon,linespec)
h = plot3m(lat,lon,PropertyName,PropertyValue,...)
```

Description

`h = plot3m(lat,lon,z)` displays projected line objects on the current map axes. `lat` and `lon` are the latitude and longitude coordinates, respectively, of the line object to be projected. Note that this ordering is conceptually reversed from the MATLAB `line` function, because the *vertical* (*y*) coordinate comes first. However, the ordering latitude, then longitude, is standard geographic usage. `lat` and `lon` must be the same size, and in the `AngleUnits` of the map axes. `z` is the altitude data associated with each point in `lat` and `lon`. The object handle for the displayed line can be returned in `h`.

The units of `z` are arbitrary, except when using the `Globe` projection. In the case of `globe`, `z` should have the same units as the radius of the earth or semimajor axis specified in the `'geoid'` (reference ellipsoid) property of the map axes. This implies that when the reference ellipsoid is a unit sphere, the units of `z` are earth radii.


`h = plot3m(lat,lon,linespec)` where `linespec` specifies the line style.

`h = plot3m(lat,lon,PropertyName,PropertyValue,...)` allows the specification of any number of property name/property value pairs for any properties recognized by the MATLAB `line` function except for `XData`, `YData`, and `ZData`.

Examples

```
axesm sinusoid; framem; view(3)
[lats,longs] = interpnm([45 -45 -45 45 45 -45]',...
    [-100 -100 100 100 -100 -100]',1);
```

```
z = (1:671)'/100;  
plot3m(lats, longs, z, 'm')
```



Tips

`plot3m` is the mapping equivalent of the MATLAB `plot3` function.

See Also

`linem` | `plot3` | `plotm`

plotm

Project 2-D lines and points on map axes

`plotm` is the mapping equivalent of the MATLAB `plot` function.

Syntax

```
plotm(lat,lon)
plotm([lat lon])
plotm(lat,lon,linetype)
plotm(lat,lon,Name,Value)
h = plotm( ___ )
```

Description

`plotm(lat,lon)` displays projected line objects on the current map axes. `lat` and `lon` are the latitude and longitude coordinates, respectively, of the line object to be projected. This ordering of latitude then longitude is standard geographic usage. However, this ordering is conceptually reversed from the MATLAB `line` function, in which the *horizontal* (x) coordinate comes first.

`plotm([lat lon])` allows the latitude and longitude coordinates to be packed into a single two-column matrix.

`plotm(lat,lon,linetype)` specifies the line style, `linetype`.

`plotm(lat,lon,Name,Value)` uses name-value pair arguments to specify any number of Line Properties except for `XData`, `YData`, and `ZData`. `Name` is the property name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1,Value1,...,NameN,ValueN`. Property names can be abbreviated, and case does not matter.


`h = plotm(___)` returns a handle to the displayed line.

Examples

Display Projected Line Object on Map Axes

Display coastline data on map axes.

```
load coastlines  
axesm sinusoid;  
framem  
plotm(coastlat,coastlon,'g')
```



Input Arguments

lat, lon — Latitude or longitude vector

numeric vector

Latitude or longitude vector, specified as a numeric vector. The vector may contain embedded NaNs to delimit individual lines or polygon parts. `lat` and `lon` must be of equal length, and in the `AngleUnits` of the map axes.

linetype — Line specification

LineStyle

Line specification that controls the style of the line, specified as a `LineStyle`.

Output Arguments

h — Handle to displayed line

handle object

Handle to the displayed line, returned as a handle to a MATLAB graphics object.

See Also

`linem` | `plot` | `plot3m`

Introduced before R2006a

polcmap

Create colormap appropriate to political regions

Syntax

```
polcmap
polcmap(ncolors)
polcmap(ncolors,maxsat)
polcmap(ncolors,huelimits,saturationlimits,valuelimits)
cmap = polcmap( ___ )
```

Description

`polcmap` applies a random, muted colormap to the current figure. The size of the colormap is the same as the existing colormap.

`polcmap(ncolors)` creates a colormap with the specified number of colors.

`polcmap(ncolors,maxsat)` controls the maximum saturation of the colors.

`polcmap(ncolors,huelimits,saturationlimits,valuelimits)` controls the hue, saturation, and value of the colors. `polcmap` randomly selects values within the limit vectors. These are two-element vectors of the form `[min max]`. Valid values range from 0 to 1. As the hue varies from 0 to 1, the resulting color varies from red, through yellow, green, cyan, blue, and magenta, back to red. When the saturation is 0, the colors are unsaturated; they are simply shades of gray. When the saturation is 1, the colors are fully saturated; they contain no white component. As the value varies from 0 to 1, the brightness increases.


`cmap = polcmap(___)` returns the colormap without applying it to the figure.

Examples

Color Patches with SymbolSpec Created Using polcmap

Create an empty map axes with a Lambert Conformal Conic projection and map limits covering Texas.

```
figure  
usamap('texas')
```



Read vector features, such as state boundaries, from a shapefile.


```
states = shaperead('usastatelo.shp', 'UseGeoCoords', true);
```

Define the colors you want to apply to the shapes (states) in a symbol specification. Use `polcmap` to create a color map the same size as the number of elements in the `states` array. `polcmap` creates a palette of muted colors.

```
faceColors = makesymbolspec('Polygon',...  
    {'INDEX', [1 numel(states)], 'FaceColor', ...  
    polcmap(numel(states))});
```

Display the map using the symbol specification to color the patches (states) in the map. The colors you obtain for this example can vary each time you run this example because `polcmap` computes them randomly.

```
geoshow(states, 'DisplayType', 'polygon', 'SymbolSpec', faceColors)
```



Input Arguments

ncolors — Number of colors in the color map

numeric scalar

Number of colors in the color map, specified as a numeric scalar.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64` | `logical`

maxsat — Maximum saturation of colors

0.5 (default) | numeric scalar

Maximum saturation of colors, specified as a numeric scalar. Larger maximum saturation values produce brighter, more saturated colors.

Data Types: `single` | `double` | `logical` | `char`

huelimits — Color range limits

[0 1] (default) | two-element vector

Color range limits, specified as a two-element vector of the form `[min max]`. Values range from 0 to 1.0. As the hue varies from 0 to 1, the resulting color varies from red, through yellow, green, cyan, blue, and magenta, back to red.

Data Types: `single` | `double`

saturationlimits — Color saturation limits

[.25 .5] (default) | two-element vector

Color saturation limits, specified as a two-element vector of the form `[min max]`. Values range from 0 to 1.0. When the saturation is 0, the colors are unsaturated; they are simply shades of gray. When the saturation is 1, the colors are fully saturated; they contain no white component.

Data Types: `single` | `double`

valuelimits — Brightness of colors

[1 1] (default) | two-element vector

Brightness of colors, specified as a two-element vector of the form `[min max]`. Values range from 0 to 1.0. As the value varies from 0 to 1, the brightness increases.

Data Types: `single` | `double`

Output Arguments

cmap — Colormap

m-by-3 numeric array

Colormap, returned as an *m*-by-3 numeric array of class `double` or class `single`, depending on the type of the input.

Tips

- You cannot use `polcmap` to alter the colors of displayed patches drawn by `geoshow` or `mapshow`. The patches must have been rendered by `displaym`. However, you can color patches using `polcmap` when you call `geoshow` or `mapshow` (see “Color Patches with SymbolSpec Created Using `polcmap`” on page 1-1100).

See Also

`colormap` | `demcmap`

Introduced before R2006a

poly2ccw

Convert polygon contour to counterclockwise vertex ordering

Syntax

```
[x2, y2] = poly2ccw(x1, y1)
```

Description

`[x2, y2] = poly2ccw(x1, y1)` arranges the vertices in the polygonal contour (`x1`, `y1`) in counterclockwise order, returning the result in `x2` and `y2`. If `x1` and `y1` can contain multiple contours, represented either as NaN-separated vectors or as cell arrays, then each contour is converted to clockwise ordering. `x2` and `y2` have the same format (NaN-separated vectors or cell arrays) as `x1` and `y1`.

Examples

Convert a clockwise-ordered square to counterclockwise ordering.

```
x1 = [0 0 1 1 0];  
y1 = [0 1 1 0 0];  
ispolycw(x1, y1)
```

```
ans =  
     1
```

```
[x2, y2] = poly2ccw(x1, y1);  
ispolycw(x2, y2)  
ans =  
     0
```

See also

`ispolycw`, `poly2cw`, `polyshape`

Introduced before R2006a

poly2cw

Convert polygon contour to clockwise vertex ordering

Syntax

```
[x2, y2] = poly2cw(x1, y1)
```

Description

`[x2, y2] = poly2cw(x1, y1)` arranges the vertices in the polygonal contour (`x1, y1`) in clockwise order, returning the result in `x2` and `y2`. If `x1` and `y1` can contain multiple contours, represented either as NaN-separated vectors or as cell arrays, then each contour is converted to clockwise ordering. `x2` and `y2` have the same format (NaN-separated vectors or cell arrays) as `x1` and `y1`.

Examples

Convert a counterclockwise-ordered square to clockwise ordering.

```
x1 = [0 1 1 0 0];  
y1 = [0 0 1 1 0];  
ispolycw(x1, y1)
```

```
ans =  
     0
```

```
[x2, y2] = poly2cw(x1, y1);  
ispolycw(x2, y2)
```

```
ans =  
     1
```

See also

`ispolycw`, `poly2ccw`, `polyshape`

Introduced before R2006a

poly2fv

Convert polygonal region to patch faces and vertices

Syntax

```
[F,V] = poly2fv(x,y)
```

Description

`[F,V] = poly2fv(x,y)` converts the polygonal region represented by the contours (x,y) into a faces matrix, F , and a vertices matrix, V , that can be used with the `patch` function to display the region. If the polygon represented by x and y has multiple parts, either the NaN-separated vector format or the cell array format may be used. The `poly2fv` function creates triangular faces.

Most Mapping Toolbox functions adhere to the convention that individual contours with clockwise-ordered vertices are external contours and individual contours with counterclockwise-ordered vertices are internal contours. Although the `poly2fv` function ignores vertex order, you should follow the convention when creating contours to ensure consistency with other functions.

Examples

Display a rectangular region with two holes using a single patch object.

```
% External contour, rectangle.  
x1 = [0 0 6 6 0];  
y1 = [0 3 3 0 0];  
  
% First hole contour, square.  
x2 = [1 2 2 1 1];  
y2 = [1 1 2 2 1];  
  
% Second hole contour, triangle.  
x3 = [4 5 4 4];
```

```
y3 = [1 1 2 1];  
  
% Compute face and vertex matrices.  
[f, v] = poly2fv({x1, x2, x3}, {y1, y2, y3});  
  
% Display the patch.  
patch('Faces', f, 'Vertices', v, 'FaceColor', 'r', ...  
      'EdgeColor', 'none');  
axis off, axis equal
```

See also

ispolycw, patch, poly2cw, poly2ccw, polyshape

Introduced before R2006a

polybool

Set operations on polygonal regions

Note `polybool` is not recommended. Use `polyshape` instead.

To replace calls to `polybool`, create `polyshape` objects to represent the shapes, call the appropriate `polyshape` object function for the equivalent Boolean operation, and then call the `polyshape` boundary object function. For example, this call to `polybool` specifies the union operation as the first argument.

```
[Cx,Cy] = polybool('union',Ax,Ay,Bx,By)
```

To update this usage, create separate `polyshape` objects for each shape and then use the union object function associated with the `polyshape` object. `polyshape` supports the Boolean operations supported by `polybool`: union, intersection, subtraction, and exclusive OR. Use the `polyshape` boundary object function to return `Cx` and `Cy`. See `polyshape` for a complete list of object functions, including `plot`.

```
A = polyshape(Ax,Ay,'Simplify',false);  
B = polyshape(Bx,By,'Simplify',false);  
C = union(A,B);  
[Cx,Cy] = boundary(C);
```

Note that the polygon vertex order is likely to differ between the output from `polybool` and the output from the call to `boundary`, because there is no single right answer. (Even in a simple one-region polygon, the vertices can be permuted cyclically without affecting the underlying geometry.) In addition, if the geometries of the inputs are not perfectly clean (free from self-intersections, etc.), then the `polyshape` union operation may make small changes that are not necessarily performed in `polybool`.

Syntax

```
[x,y] = polybool(flag,x1,y1,x2,y2)
```

Description

`[x,y] = polybool(flag,x1,y1,x2,y2)` performs the polygon set operation identified by `flag`. The result is output using the same format as the input. Geographic data that encompasses a pole cannot be used directly. Use `flatearthpoly` to convert polygons that contain a pole to Cartesian coordinates.

Most Mapping Toolbox functions adhere to the convention that individual contours with clockwise-ordered vertices are external contours and individual contours with counterclockwise-ordered vertices are internal contours. Although the `polybool` function ignores vertex order, follow this convention when creating contours to ensure consistency with other functions.

Examples

Set Operations on Two Overlapping Circular Regions

```
theta = linspace(0, 2*pi, 100);
x1 = cos(theta) - 0.5;
y1 = -sin(theta);    % -sin(theta) to make a clockwise contour
x2 = x1 + 1;
y2 = y1;
[xa, ya] = polybool('union', x1, y1, x2, y2);
[xb, yb] = polybool('intersection', x1, y1, x2, y2);
[xc, yc] = polybool('xor', x1, y1, x2, y2);
[xd, yd] = polybool('subtraction', x1, y1, x2, y2);


subplot(2, 2, 1)
patch(xa, ya, 1, 'FaceColor', 'r')
axis equal, axis off, hold on
plot(x1, y1, x2, y2, 'Color', 'k')
title('Union')

subplot(2, 2, 2)
patch(xb, yb, 1, 'FaceColor', 'r')
axis equal, axis off, hold on
plot(x1, y1, x2, y2, 'Color', 'k')
title('Intersection')

subplot(2, 2, 3)
```

```
% The output of the exclusive-or operation consists of disjoint
% regions. It can be plotted as a single patch object using the
% face-vertex form. Use poly2fv to convert a polygonal region
% to face-vertex form.
[f, v] = poly2fv(xc, yc);
patch('Faces', f, 'Vertices', v, 'FaceColor', 'r', ...
      'EdgeColor', 'none')
axis equal, axis off, hold on
plot(x1, y1, x2, y2, 'Color', 'k')
title('Exclusive Or')

subplot(2, 2, 4)
patch(xd, yd, 1, 'FaceColor', 'r')
axis equal, axis off, hold on
plot(x1, y1, x2, y2, 'Color', 'k')
title('Subtraction')
```



Set Operations on Regions with Holes

```
Ax = {[1 1 6 6 1], [2 5 5 2 2], [2 5 5 2 2]};  
Ay = {[1 6 6 1 1], [2 2 3 3 2], [4 4 5 5 4]};  
subplot(2, 3, 1)  
[f, v] = poly2fv(Ax, Ay);  
patch('Faces', f, 'Vertices', v, 'FaceColor', 'r', ...  
      'EdgeColor', 'none')  
axis equal, axis off, axis([0 7 0 7]), hold on  
for k = 1:numel(Ax), plot(Ax{k}, Ay{k}, 'Color', 'k'), end  
title('A')
```

```

Bx = {[0 0 7 7 0], [1 3 3 1 1], [4 6 6 4 4]};
By = {[0 7 7 0 0], [1 1 6 6 1], [1 1 6 6 1]};
subplot(2, 3, 4);
[f, v] = poly2fv(Bx, By);
patch('Faces', f, 'Vertices', v, 'FaceColor', 'r', ...
      'EdgeColor', 'none')
axis equal, axis off, axis([0 7 0 7]), hold on
for k = 1:numel(Bx), plot(Bx{k}, By{k}, 'Color', 'k'), end
title('B')

subplot(2, 3, 2)
[Cx, Cy] = polybool('union', Ax, Ay, Bx, By);
[f, v] = poly2fv(Cx, Cy);
patch('Faces', f, 'Vertices', v, 'FaceColor', 'r', ...
      'EdgeColor', 'none')
axis equal, axis off, axis([0 7 0 7]), hold on
for k = 1:numel(Cx), plot(Cx{k}, Cy{k}, 'Color', 'k'), end
title('A \cup B')


subplot(2, 3, 3)
[Dx, Dy] = polybool('intersection', Ax, Ay, Bx, By);
[f, v] = poly2fv(Dx, Dy);
patch('Faces', f, 'Vertices', v, 'FaceColor', 'r', ...
      'EdgeColor', 'none')
axis equal, axis off, axis([0 7 0 7]), hold on
for k = 1:numel(Dx), plot(Dx{k}, Dy{k}, 'Color', 'k'), end
title('A \cap B')

subplot(2, 3, 5)
[Ex, Ey] = polybool('subtraction', Ax, Ay, Bx, By);
[f, v] = poly2fv(Ex, Ey);
patch('Faces', f, 'Vertices', v, 'FaceColor', 'r', ...
      'EdgeColor', 'none')
axis equal, axis off, axis([0 7 0 7]), hold on
for k = 1:numel(Ex), plot(Ex{k}, Ey{k}, 'Color', 'k'), end
title('A - B')

subplot(2, 3, 6)
[Fx, Fy] = polybool('xor', Ax, Ay, Bx, By);
[f, v] = poly2fv(Fx, Fy);
patch('Faces', f, 'Vertices', v, 'FaceColor', 'r', ...
      'EdgeColor', 'none')
axis equal, axis off, axis([0 7 0 7]), hold on

```

```
for k = 1:numel(Fx), plot(Fx{k}, Fy{k}, 'Color', 'k'), end  
title('XOR(A, B)')
```



Input Arguments

flag — Polygon set operation

'intersection' | 'and' | '&' | 'union' | 'or' | '|' | '+' | 'plus' |
'subtraction' | 'minus' | '-' | 'exclusiveor' | 'xor'

Polygon set operation, specified as one of the following values.

| Operation | | | | | |
|---------------------|----------------|---------|-----|-----|--------|
| Region intersection | 'intersection' | 'and' | '&' | | |
| Region union | 'union' | 'or' | ' ' | '+' | 'plus' |
| Region subtraction | 'subtraction' | 'minus' | '-' | | |
| Region exclusive or | 'exclusiveor' | 'xor' | | | |

Data Types: char | string

x1 — Polygon contours

NaN-delimited vectors | cell arrays

Polygon contours, specified as a NaN-delimited vector or cell array.

Data Types: double

x2 — Polygon contours

NaN-delimited vectors | cell arrays

Polygon contours, specified as a NaN-delimited vector or cell array.

Data Types: double

y1 — Polygon contours

NaN-delimited vectors | cell arrays

Polygon contours, specified as a NaN-delimited vector or cell array.

Data Types: double

y2 — Polygon contours

NaN-delimited vectors | cell arrays

Polygon contours, specified as a NaN-delimited vector or cell array.

Data Types: double

Output Arguments

x — Polygon contour after set operation

Same format as the input

Polygon contour after set operation, returned as the same format as the input, that is, a NaN-delimited vector or cell array.

y — Polygon contour after set operation

Same format as the input

Polygon contour after set operation, returned as the same format as the input, that is, a NaN-delimited vector or cell array.

Tips

- Numerical problems can occur when the polygons have a large offset from the origin. To avoid this issue, translate the coordinates to a location closer to the origin before performing the operation. Then, undo the translation after completing the operation. For example:

```
[x,y] = polybool(flag,x1-xt,y1-yt,x2-xt,y2-yt);
```

```
x = x+xt;
```

```
y = y+yt;
```

See Also

[bufferm](#) | [flatearthpoly](#) | [ispolycw](#) | [poly2ccw](#) | [poly2cw](#) | [poly2fv](#) | [polyjoin](#) | [polyshape](#) | [polysplit](#)

Introduced before R2006a

polycut

Polygon branch cuts for holes

Syntax

```
[lat2, long2] = polycut(lat, long)
```

Description

`[lat2, long2] = polycut(lat, long)` connects the contour and holes of polygons using optimal branch cuts. Polygons are input as **NaN**-delimited vectors, or as cell arrays containing individual polygons in each element with the outer face separated from the subsequent inner faces by **NaNs**. Multiple polygons outputs are separated by **NaNs**.

See Also

`polyjoin` | `polyshape` | `polysplit`

Introduced before R2006a

polyjoin

Convert line or polygon parts from cell arrays to vector form

Syntax

```
[lat,lon] = polyjoin(latcells,loncells)
```

Description

`[lat,lon] = polyjoin(latcells,loncells)` converts polygons from cell array format to column vector format. In cell array format, each element of the cell array is a vector that defines a separate polygon.

Examples

```
latcells = {[1 2 3]'; 4; [5 6 7 8 NaN 9]'};  
loncells = {[9 8 7]'; 6; [5 4 3 2 NaN 1]'};  
[lat,lon] = polyjoin(latcells,loncells);  
[lat lon]
```

```
ans =  
     1     9  
     2     8  
     3     7  
    NaN    NaN  
     4     6  
    NaN    NaN  
     5     5  
     6     4  
     7     3  
     8     2  
    NaN    NaN  
     9     1
```

Tips

A polygon may consist of an outer contour followed by holes separated with NaNs. In vector format, each vector may contain multiple faces separated by NaNs. There is no structural distinction between outer contours and holes in vector format.

See Also

`polyshape` | `polysplit`

Introduced before R2006a

polymerge

Merge line segments with matching endpoints

Syntax

```
[latMerged, lonMerged] = polymerge(lat, lon)
[latMerged, lonMerged] = polymerge(lat, lon, tol)
[latMerged, lonMerged] = polymerge(lat, lon, tol, outputFormat)
```

Description

`[latMerged, lonMerged] = polymerge(lat, lon)` accepts a multipart line in latitude-longitude with vertices stored in arrays `lat` and `lon`, and merges the parts wherever a pair of end points coincide. For this purpose, an end point can be either the first or last vertex in a given part. When a pair of parts are merged, they are combined into a single part and the duplicate common vertex is removed. If two first vertices coincide or two last vertices coincide, then the vertex order of one of the parts will be reversed. A merge is applied anywhere that the end points of exactly two distinct parts coincide, so that an indefinite number of parts can be chained together in a single call to `polymerge`. If three or more distinct parts share a common end point, however, the choice of which parts to merge is ambiguous and therefore none of the corresponding parts are connected at that common point.

The inputs `lat` and `lon` can be column or row vectors with NaN-separated parts (and identical NaN locations in each array), or they can be cell arrays with each part in a separate cell. The form of the output arrays, `latMerged` and `lonMerged`, matches the inputs in this regard.

`[latMerged, lonMerged] = polymerge(lat, lon, tol)` combines line segments whose endpoints are separated by less than the circular tolerance, `tol`. `tol` has the same units as the polygon input.

`[latMerged, lonMerged] = polymerge(lat, lon, tol, outputFormat)` allows you to request either the NaN-separated vector form for the output (set `outputFormat` to `'vector'`), or the cell array form (set `outputFormat` to `'cell'`).

Examples

```
lat = [1 2 3 NaN 6 7 8 9 NaN 6 5 4 3 NaN 12 13 14 ...  
      NaN 9 10 11 12]';  
lon = lat;  
[lat2, lon2] = polymerge(lat, lon);  
[lat2, lon2]
```

```
ans =
```

```
 1     1  
 2     2  
 3     3  
 4     4  
 5     5  
 6     6  
 7     7  
 8     8  
 9     9  
10    10  
11    11  
12    12  
13    13  
14    14  
NaN   NaN
```

See Also

`polyjoin` | `polysplit`

Introduced before R2006a

polysplit

Convert line or polygon parts from vector form to cell arrays

Syntax

```
[latcells,loncells] = polysplit(lat,lon)
```

Description

`[latcells,loncells] = polysplit(lat,lon)` returns the NaN-delimited segments of the vectors `lat` and `lon` as N-by-1 cell arrays with one polygon segment per cell. `lat` and `lon` must be the same size and have identically-placed NaNs. The polygon segments are column vectors if `lat` and `lon` are column vectors, and row vectors otherwise.

Examples

```
lat = [1 2 3 NaN 4 NaN 5 6 7 8 9]';  
lon = [9 8 7 NaN 6 NaN 5 4 3 2 1]';  
[latcells,loncells] = polysplit(lat,lon);  
[latcells loncells]
```

```
ans =  
    [3x1 double]    [3x1 double]  
    [         4]    [         6]  
    [5x1 double]    [5x1 double]
```

See Also

[isshapemultipart](#) | [polyjoin](#) | [polyshape](#)

Introduced before R2006a

polyxpoly

Intersection points for lines or polygon edges

Syntax

```
[xi,yi] = polyxpoly(x1,y1,x2,y2)
[xi,yi,ii] = polyxpoly(____)
[xi,yi] = polyxpoly(____,'unique')
```

Description

`[xi,yi] = polyxpoly(x1,y1,x2,y2)` returns the intersection points of two polylines in a planar, Cartesian system, with vertices defined by `x1`, `y1`, `x2` and `y2`. The output arguments, `xi` and `yi`, contain the x - and y -coordinates of each point at which a segment of the first polyline intersects a segment of the second. In the case of overlapping, collinear segments, the intersection is actually a line segment rather than a point, and both endpoints are included in `xi`, `yi`.

`[xi,yi,ii] = polyxpoly(____)` returns a two-column array of line segment indices corresponding to the intersection points. The k -th row of `ii` indicates which polyline segments give rise to the intersection point `xi(k)`, `yi(k)`.

To remember how these indices work, just think of segments and vertices as fence sections and posts. The i -th fence section connects the i -th post to the $(i+1)$ -th post. In general, letting i and j denote the scalar values comprised by the k -th row of `ii`, the intersection indicated by that row occurs where the i -th segment of the first polyline intersects the j -th segment of the second polyline. But when an intersection falls precisely on a vertex of the first polyline, then i is the index of that vertex. Likewise with the second polyline and the index j . In the case of an intersection at the i -th vertex of the first line, for example, `xi(k)` equals `x1(i)` and `yi(k)` equals `y1(i)`. In the case of intersections between vertices, i and j can be interpreted as follows: the segment connecting `x1(i)`, `y1(i)` to `x1(i+1)`, `y1(i+1)` intersects the segment connecting `x2(j)`, `y2(j)` to `x2(j+1)`, `y2(j+1)` at the point `xi(k)`, `yi(k)`.

`[xi,yi] = polyxpoly(____,'unique')` filters out duplicate intersections, which may result if the input polylines are self-intersecting.

Examples

Find Intersection Points Between Rectangle and Polyline

Define and fill a rectangular area in the plane.


```
xlimit = [3 13];  
ylimit = [2 8];  
xbox = xlimit([1 1 2 2 1]);  
ybox = ylimit([1 2 2 1 1]);  
mapshow(xbox,ybox, 'DisplayType', 'polygon', 'LineStyle', 'none')
```

Define and display a two-part polyline.

```
x = [0 6 4 8 8 10 14 10 14 NaN 4 4 6 9 15];  
y = [4 6 10 11 7 6 10 10 6 NaN 0 3 4 3 6];  
mapshow(x,y, 'Marker', '+')
```

Intersect the polyline with the rectangle.

```
[xi,yi] = polyxpoly(x,y,xbox,ybox);  
mapshow(xi,yi, 'DisplayType', 'point', 'Marker', 'o')
```

Display the intersection points; note that the point (12, 8) appears twice because of a self-intersection near the end of the first part of the polyline.

```
[xi yi]
```

```
ans = 8x2
```

```

3.0000    5.0000
5.0000    8.0000
8.0000    8.0000
12.0000   8.0000
12.0000   8.0000
13.0000   7.0000
13.0000   5.0000

```

```
4.0000 2.0000
```

You can suppress this duplicate point by using the 'unique' option.

```
[xi,yi] = polyxpoly(x,y,xbox,ybox,'unique');  
[xi yi]
```

```
ans = 7×2
```

```
3.0000 5.0000  
5.0000 8.0000  
8.0000 8.0000  
12.0000 8.0000  
13.0000 7.0000  
13.0000 5.0000  
4.0000 2.0000
```

Find Intersection Points Between State Border and Small Circle

Display a map of the state of California.


```
california = shaperead('usastatehi',...  
    'UseGeoCoords',true,...  
    'Selector',{@(name) strcmpi(name,'California'),'Name'});  
usamap('california')  
geoshow(california,'FaceColor','none')
```

Define a small circle centered off the coast of California.

```
lat0 = 37;  
lon0 = -122;  
rad = 500;  
[latc,lonc] = scircle1(lat0,lon0,km2deg(rad));  
plotm(lat0,lon0,'r*')  
plotm(latc,lonc,'r')
```

Find the intersection points between the state of California and the small circle.

```
[loni, lati] = polyxpoly(lonc, latc, ...  
    california.Lon',california.Lat');  
plotm(lati, loni, 'bo')
```



Input Arguments

x1, y1, x2, y2 — Coordinates of polylines

numeric vector

x- or y-coordinates of points in the first or second polyline, specified as a numeric vector. For a given polyline, the x- and y-coordinate vectors must be the same length.

Output Arguments

xi, yi — Coordinates of intersection points

numeric column vector

x- or y-coordinates of intersection points, specified as a numeric column vector.

ii — line segment indices

numeric vector

Line segment indices of intersection points, specified as a numeric vector.

See Also

[crossfix](#) | [gcxgc](#) | [gcxsc](#) | [navfix](#) | [rhxrh](#) | [scxsc](#)

Introduced before R2006a

previewmap

View map at printed size

Description

The appearance of a map onscreen can differ from the final printed output. This results from the difference in the size and shape of the figure window and the area the figure occupies on the printed page. A map that appears readable on screen might be cluttered when the printed output is smaller. Likewise, the relative position of multiple axes can appear different when printed. This function resizes the figure to the printed size.

Examples

Is the text small enough to avoid overlapping in a map of Europe?

```
figure
worldmap europe
land=shaperead('landareas.shp','UseGeoCoords',true);
geoshow([land.Lat],[land.Lon])
m=gcm;
latlim = m.maplatlimit;
lonlim = m.maplonlimit;
BoundingBox = [lonlim(1) latlim(1);lonlim(2) latlim(2)];
cities=shaperead('worldcities.shp', ...
    'BoundingBox',BoundingBox,'UseGeoCoords',true);
for index=1:numel(cities)
    h=textm(cities(index).Lat, cities(index).Lon, ...
        cities(index).Name);
    trimcart(h)
    rotatetext(h)
end
orient landscape
tightmap
axis off
previewmap
```


Introduced before R2006a

project

Project displayed map graphics object

Note `project` will be removed in a future release.

Syntax

```
project(h)
project(h, 'xy')
project(h, 'yx')
```

Description

`project(h)` takes unprojected objects with handles `h` that are displayed on map axes and projects them. For example, `project` takes a line created on a map axes with the `plot` function and projects it as though it had been created with the `plotm` function. This can be useful if a standard MATLAB function was accidentally executed. The map structure of the existing map axes determines the specifics of the projection. If `h` is the handle of the map axes, then all the children of `h` are projected. Do not attempt this if any children of `h` have already been projected!


`project(h, 'xy')` specifies that the `XData` of the unprojected objects corresponds to longitudes and the `YData` to latitudes. This is the default assumption.

`project(h, 'yx')` specifies that the `XData` of the unprojected objects corresponds to latitudes and the `YData` to longitudes.


Examples

Create an axes, plot a line, then project it:

```
axesm('bonne', 'AngleUnits', 'radians'); framem;
h = plot([-1 -.5 0 .5 1], [-1 -.5 0 .5 1]);
```

project(h)



The line is straight in x - y space, but when converted to a projected map object, it bends with the projection.

See Also

Introduced before R2006a

projfwd

Forward map projection using PROJ .4 map projection library

Syntax

```
[x,y] = projfwd(proj,lat,lon)
```

Description

`[x,y] = projfwd(proj,lat,lon)` returns the x and y map coordinates from the forward projection transformation. `proj` is a structure defining the map projection. `proj` can be an `mstruct` or a `GeoTIFF info` structure. `lat` and `lon` are arrays of the latitude and longitude coordinates.

For a complete list of `GeoTIFF info` and map projection structures that you can use with `projinv`, see the reference page for `projlist`.

Examples

Overlay Boundary of Massachusetts on Orthophoto of Boston

Read vector data for state boundary of Massachusetts (in latitude and longitude).

```
S = shaperead('usastatehi', 'UseGeoCoords', true, ...
    'Selector',{@(name) strcmpi(name,'Massachusetts'), 'Name'});
```

Obtain the projection structure for the orthophoto and project the state boundary vectors to it (Massachusetts State Plane coordinate system, U.S. Survey Feet).


```
proj = geotiffinfo('boston.tif');
lat = [S.Lat];
lon = [S.Lon];
[x, y] = projfwd(proj, lat, lon);
```

Read and display the 'boston.tif' orthophoto image.

```
[RGB, R, bbox] = geotiffread('boston.tif');  
figure  
mapshow(RGB, R)  
xlabel('MA Mainland State Plane easting, survey feet')  
ylabel('MA Mainland State Plane northing, survey feet')
```

Overlay the state boundary and set map limits to show a little more detail.

```
hold on  
mapshow(gca, x, y, 'Color', 'black', 'LineWidth', 2.0)  
set(gca, 'XLim', [ 645000,  895000], ...  
        'YLim', [2865000, 3040000]);
```



boston.tif image copyright © GeoEye, all rights reserved.

Input Arguments

proj — Map projection

scalar structure

Map projection, specified as a scalar map projection structure (`mstruct`) or GeoTIFF info structure.

Data Types: `struct`

lat — Geodetic latitudes

scalar value | vector | matrix | N-D array

Geodetic latitudes of one or more points, specified as a scalar value, vector, matrix, or N-D array, in units of degrees. Size must match the size of the `lon` input.

Data Types: `single` | `double`

lon — Longitudes

scalar value | vector | matrix | N-D array

Longitudes of one or more points, specified as a scalar value, vector, matrix, or N-D array, in units of degrees. Size must match the size of the `lat` input.

Data Types: `single` | `double`

Output Arguments

x — Projected x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the projected coordinate system, returned as a scalar value, vector, matrix, or N-D array.

y — Projected y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the projected coordinate system, returned as a scalar value, vector, matrix, or N-D array.

See Also

`geotiffinfo` | `mfwdtran` | `minvtran` | `projinv` | `projlist`

Introduced before R2006a

projinv

Inverse map projection using PROJ.4 map projection library

Syntax

```
[lat,lon] = projinv(proj,x,y)
```

Description

[lat,lon] = projinv(proj,x,y) returns the latitude and longitude values from the inverse projection transformation. proj is a structure defining the map projection. proj can be a map projection mstruct or a GeoTIFF info structure. x and y are x-y map coordinate arrays. For a complete list of GeoTIFF info and map projection structures that you can use with projinv, see the reference page for projlist.

Examples

Display Boston Orthophoto on a Mercator Projection

Import the Boston roads from the shapefile and obtain the projection structure from the 'boston.tif' orthophoto.

```
roads = shaperead('boston_roads.shp');  
proj = geotiffinfo('boston.tif');
```

Convert the road coordinates to the projection's length unit. In this example, coordinates in the roads shapefile are in meters. The units of length in the projected coordinate system is US Survey Feet, documented in the value of the UOMLength field of the projection structure.

```
x = [roads.X] * unitsratio('survey feet','meter');  
y = [roads.Y] * unitsratio('survey feet','meter');
```

```
[roadsLat, roadsLon] = projinv(proj, x, y);
```

Read the `boston_ovr.jpg` image and worldfile.

```
RGB = imread('boston_ovr.jpg');  
R = worldfileread(getworldfilename('boston_ovr.jpg'));
```

Read state boundary vectors for Massachusetts from the `usastatehi` shapefile using a selector to eliminate other states.


```
S = shaperead('usastatehi', 'UseGeoCoords', true, ...  
    'Selector',{@(name) strcmpi(name,'Massachusetts')}, 'Name');
```

Open a figure with a Mercator projection and display the image, state boundary, and roads.

```
figure  
axesm('mercator')  
  
geoshow(RGB, R)  
geoshow(S.Lat, S.Lon, 'Color','red')  
geoshow(roadsLat, roadsLon, 'Color', 'green')
```

Set the map boundary to the image's northern, western, and southern limits, and the eastern limit of the state boundary within the image latitude bounding box.

```
[lon, lat] = mapoutline(R, size(RGB(:,:,1)));  
ltvals = find((S.Lat>=min(lat(:))) & (S.Lat<=max(lat(:))));  
setm(gca, 'maplonlimit', [min(lon(:)) max(S.Lon(ltvals))], ...  
    'maplatlimit', [min(lat(:)) max(lat(:))])  
tightmap
```

boston_ovr.jpg image copyright © GeoEye, all rights reserved.

Input Arguments

proj — Map projection

scalar structure

Map projection, specified as a scalar map projection structure (`mstruct`) or GeoTIFF info structure.

Data Types: `struct`

x — Projected x-coordinates

scalar value | vector | matrix | N-D array

x-coordinates of one or more points in the projected coordinate system, specified as a scalar value, vector, matrix, or N-D array. Size must match the size of the y input.

Data Types: single | double

y — Projected y-coordinates

scalar value | vector | matrix | N-D array

y-coordinates of one or more points in the projected coordinate system, specified as a scalar value, vector, matrix, or N-D array. Size must match the size of the x input.

Data Types: single | double

Output Arguments

lat — Geodetic latitudes

scalar value | vector | matrix | N-D array

Geodetic latitudes of one or more points, returned as a scalar value, vector, matrix, or N-D array, in units of degrees.

lon — Longitude

scalar value | vector | matrix | N-D array

Longitudes of one or more points, returned as a scalar value, vector, matrix, or N-D array, in units of degrees.

See Also

geotiffinfo | mfwdtran | minvtran | projfwd | projlist

Introduced before R2006a

projlist

Map projections supported by `proj fwd` and `proj inv`

Syntax

```
projlist(listmode)
S = projlist(listmode)
```

Description

`projlist(listmode)` displays a table of projection names, IDs, and availability. `listmode` can be `'mapprojection'`, `'geotiff'`, `'geotiff2mstruct'`, or `'all'`. The default value is `'mapprojection'`.

`S = projlist(listmode)` returns a structure array containing projection names, IDs, and availability. The output of `projlist` for each `listmode` is described below:

- `mapprojection` — Lists the map projection IDs that are available for use with `proj fwd` and `proj inv`. The output structure contains the fields
 - `Name` — Projection name
 - `MapProjection` — Projection ID
- `geotiff` — Lists the GeoTIFF projection IDs that are available for use with `proj fwd` and `proj inv`. The output structure contains the fields
 - `GeoTIFF` — GeoTIFF projection ID .
 - `Available`— Logical array with values 1 or 0
- `geotiff2mstruct` — Lists the GeoTIFF projection IDs that are available for use with `geotiff2mstruct`. The output structure contains the fields
 - `GeoTIFF` — GeoTIFF projection ID
 - `MapProjection` — Projection ID
- `all` — Lists the map and GeoTIFF projection IDs that are available for use with `proj fwd` and `proj inv`. The output structure contains the fields

- `GeoTIFF` — GeoTIFF projection ID
- `MapProjection` — Projection ID
- `info` — Logical array with values 1 or 0
- `mstruct` — Logical array with values 1 or 0

Examples

```
s=projlist
```

```
s =  
1x19 struct array with fields:  
    Name  
    MapProjection
```

```
s=projlist('geotiff2mstruct')
```

```
s =  
1x19 struct array with fields:  
    GeoTIFF  
    MapProjection
```

Tips

`projfwd` and `projinv` can be used to process certain forward or inverse map projections. These functions are implemented in C using the PROJ.4 library. `projlist` provides a convenient list of the projections that can be used with `projfwd` or `projinv`. Because `projfwd` and `projinv` accept either a map projection structure (`mstruct`) or a GeoTIFF info structure, `projlist` provides separate lists for each case. It can also list the projections for which a GeoTIFF info structure can be converted to an `mstruct`.

See Also

`geotiff2mstruct` | `maplist` | `maps` | `projfwd` | `projinv`

Introduced before R2006a

properties

Return property names of geographic or planar vector

Syntax

```
prop = properties(v)
```

Description

`prop = properties(v)` returns the property names of the geographic or planar vector `v`.

Examples

View All Properties of a Mapshape Vector

Create a mapshape vector.

```
ms = mapshape(shaperead('tsunamis', 'UseGeo', true));
```

Display all properties of the mapshape vector. This includes the Geometry and Metadata collection properties, the X and Y required mapshape Vertex properties, and all dynamic properties.

```
properties(ms)
```

Properties for class mapshape:

```
Geometry  
Metadata  
X  
Y  
Lon  
Lat  
Year
```

Month
Day
Hour
Minute
Second
Val_Code
Validity
Cause_Code
Cause
Eq_Mag
Country
Location
Max_Height
Iida_Mag
Intensity
Num_Deaths
Desc_Deaths

Input Arguments

v — Geographic or planar vector

geopoint, geoshape, mappoint, or mapshape object

Geographic or planar vector, specified as a `geopoint`, `geoshape`, `mappoint`, or `mapshape` object.

Output Arguments

prop — Property names

cell array

Property names of geographic or planar vector `v`, returned as a cell array.

See Also

`disp` | `fieldnames`

Introduced in R2012a

putpole

Origin vector to place north pole at specified point

Syntax

```
origin = putpole(pole)
origin = putpole(pole,units)
```

Description

`origin = putpole(pole)` returns an `origin` vector required to transform a coordinate system in such a way as to put the true North Pole at a point specified by the three- (or two-) element vector `pole`. This vector is of the form [`latitude longitude meridian`], specifying the coordinates in the original system at which the true North Pole is to be placed in the transformed system. The meridian is the longitude upon which the new system is to be centered, which is the new pole longitude if omitted. The output is a three-element vector of the form [`latitude longitude orientation`], where the latitude and longitude are the coordinates in the untransformed system of the new origin, and the orientation is the azimuth of the true North Pole in the transformed system.

`origin = putpole(pole,units)` allows the specification of the angular units of the origin vector, where `units` is any valid angle unit. The default is 'degrees'.

Examples

Pull the North Pole down the 0° meridian by 30° to 60°N. What is the resulting origin vector?

```
origin = putpole([60 0])
origin =
    30.0000         0         0
```

This makes sense: when the pole slid down 30° , the point that was 30° north of the origin slid down to become the origin. Following is a less obvious transformation:

```
origin = putpole([60 80 0]) % constrain to original central
                        % meridian

origin =
    4.9809         0    29.6217

origin = putpole([60 80 40]) % constrain to arbitrary meridian

origin =
    4.9809    40.0000    29.6217
```

Tips

When developing transverse or oblique projections, you need transformed coordinate systems. One way to define these systems is to establish the point in the original (untransformed) system that will become the new (transformed) origin.

See Also

`neworig` | `org2pol`

Introduced before R2006a

quiver3m

Project 3-D quiver plot on map axes

Syntax

```
h = quiver3m(lat,lon,alt,dlat,dlon,dalt)
h = quiver3m(lat,lon,alt,dlat,dlon,dalt,linestyle)
h = quiver3m(lat,lon,alt,dlat,dlon,dalt,linestyle,'filled')
h = quiver3m(lat,lon,alt,dlat,dlon,dalt,scale)
h = quiver3m(lat,lon,alt,dlat,dlon,dalt,linestyle,scale)
h = quiver3m(lat,lon,alt,dlat,dlon,dalt,linestyle,scale,'filled')
```

Description

`h = quiver3m(lat,lon,alt,dlat,dlon,dalt)` displays *velocity* vectors with components (`dlat`, `dlon`, `dalt`) at the geographic points (`lat`, `lon`) and altitude `alt` on a displayed map axes. The inputs `dlat`, `dlon`, and `dalt` determine the direction of the vectors in latitude, longitude, and altitude, respectively. The function automatically determines the length of these vectors to make them as long as possible without overlap. The object handles of the displayed vectors can be returned in `h`.

`h = quiver3m(lat,lon,alt,dlat,dlon,dalt,linestyle)` where `linestyle` is a `linespec` that controls the type of line used. If you use symbols, they are plotted at the start points of the vectors, i.e., the input points (`lat`, `lon`, `alt`).

`h = quiver3m(lat,lon,alt,dlat,dlon,dalt,linestyle,'filled')` results in the filling in of any symbols specified by *linespec*.


`h = quiver3m(lat,lon,alt,dlat,dlon,dalt,scale)`, `h = quiver3m(lat,lon,alt,dlat,dlon,dalt,linestyle,scale)` and `h = quiver3m(lat,lon,alt,dlat,dlon,dalt,linestyle,scale,'filled')` alter the automatically calculated vector lengths by multiplying them by the scalar value `scale`. For example, if `scale` is 2, the displayed vectors are twice as long as they would be if `scale` were 1 (the default). When `scale` is set to 0, the automatic scaling is suppressed and the length of the vectors is determined by the inputs. In this case, the vectors are plotted from (`lat`, `lon`, `alt`) to (`lat+dlat`, `lon+dlon`, `alt+dalt`).

Examples

Plot 3-D Quiver Vectors

Plot 3-D quiver vectors from London (51.5°N,0°) and New Delhi (29°N,77.5°E), both at an altitude of 0. Suppress the automatic scaling. Terminate both vectors at an altitude of 1; the London vector should terminate 100° southward and 70° eastward, while the New Delhi vector should terminate 50° northward and 10° eastward.

```
load coastlines
axesm miller;
view(3)
plotm(coastlat,coastlon)
lat0 = [51.5,29];
lon0 = [0 77.5];
alt = [0 0];
dlat = [-40 50];
dlon = [-70 10];
dalt = [1 1];
quiver3m(lat0,lon0,alt,dlat,dlon,dalt,'m')
tightmap
```



See Also

quiver3 | quiverm

Introduced before R2006a

quiverm

Project 2-D quiver plot on map axes

Syntax

```
h = quiverm(lat,lon,deltalat,deltalon)
h = quiverm(lat,lon,deltalat,deltalon,linestyle)
h = quiverm(lat,lon,deltalat,deltalon,linestyle,'filled')
h = quiverm(lat,lon,deltalat,deltalon,scale)
h = quiverm(lat,lon,deltalat,deltalon,linestyle,scale,'filled')
```

Description

`h = quiverm(lat,lon,deltalat,deltalon)` displays *velocity* vectors with components (`deltalat`, `deltalon`) at the geographic points (`lat`, `lon`) on displayed map axes. All four inputs should be in the `AngleUnits` of the map axes. The inputs `deltalat` and `deltalon` determine the direction of the vectors in latitude and longitude, respectively. The function automatically determines the length of these vectors to make them as long as possible without overlap. The object handles of the displayed vectors can be returned in `h`.

`h = quiverm(lat,lon,deltalat,deltalon,linestyle)` allows the control of the line specification of the displayed vectors with a `linespec`. If you use symbols, they are plotted at the start points of the vectors, i.e., the input points (`lat`, `lon`).

`h = quiverm(lat,lon,deltalat,deltalon,linestyle,'filled')` results in the filling in of any symbols specified by `linestyle`.

`h = quiverm(lat,lon,deltalat,deltalon,scale)` and `h = quiverm(lat,lon,deltalat,deltalon,linestyle,scale,'filled')` alter the automatically calculated vector lengths by multiplying them by the scalar value `scale`. For example, if `scale` is 2, the displayed vectors are twice as long as they would be if `scale` were 1 (the default). When `scale` is set to 0, the automatic scaling is suppressed, and the length of the vectors is determined by the inputs. In this case, the vectors are plotted from (`lat`, `lon`) to (`lat+deltalat`, `lon+deltalon`).

Examples


Plot Quiver Vectors Corresponding to Latitude and Longitude

Load the coast lines dataset.

```
load coastlines
```


Setup an axes specifying latitude and longitude limits. Plot the coast line data.

```
axesm('eqaconic','MapLatLimit',[30 60],'MapLonLimit',[-10 10])  
frame;  
plotm(coastlat,coastlon)
```



Plot quiver vectors in a direction corresponding to +5 degrees latitude and +3 degrees longitude. Use automatic scaling.

```
lat0 = [50 39.7];  
lon0 = [-5.4 2.9];  
deltalat = [5 5];  
deltalon = [3 3];  
quiverm(lat0,lon0,deltalat,deltalon,'r')
```



See Also

[quiver](#) | [quiver3m](#)

Introduced before R2006a

rad2km

Convert spherical distance from radians to kilometers

Syntax

```
km = rad2km(rad)
km = rad2km(rad, radius)
km = rad2km(rad, sphere)
```

Description

`km = rad2km(rad)` converts distances from radians to kilometers, as measured along a great circle on a sphere with a radius of 6371 km, the mean radius of the Earth.

`km = rad2km(rad, radius)` converts distances from radians to kilometers, as measured along a great circle on a sphere having the specified radius.

`km = rad2km(rad, sphere)` converts distances from radians to kilometers, as measured along a great circle on a sphere approximating an object in the Solar System.

Input Arguments

rad — Distance in radians

numeric array

Distance in radians, specified as a numeric array.

Data Types: `single` | `double`

radius — Radius

6371 (default) | numeric scalar

Radius of sphere in units of kilometers, specified as a numeric scalar.

sphere — Sphere

'sun' | 'moon' | 'mercury' | 'venus' | 'earth' | ...

Sphere approximating an object in the Solar System, specified as one of the following values: 'sun', 'moon', 'mercury', 'venus', 'earth', 'mars', 'jupiter', 'saturn', 'uranus', 'neptune', or 'pluto'. The value of sphere is case-insensitive.

Output Arguments

km — Distance in kilometers

numeric array

Distance in kilometers, returned as a numeric array.

Data Types: `single` | `double`

See Also

`deg2km` | `deg2rad` | `km2rad` | `rad2deg` | `rad2nm` | `rad2sm`

Introduced in R2007a

radtodeg

Convert angles from radians to degrees

Note `radtodeg` is not recommended. Use `rad2deg` instead.

Syntax

```
angleInDegrees = radtodeg(angleInRadians)
```

Description

`angleInDegrees = radtodeg(angleInRadians)` converts angle units from radians to degrees. This is both an angle conversion function and a distance conversion function, because arc length can be a measure of distance in either radians or degrees (provided the radius is known).

Examples

There are 180° in π radians:

```
anglout = radtodeg(pi)
```

```
anglout =  
    180
```

See Also

`degtorad` | `fromDegrees` | `fromRadians` | `toDegrees` | `toRadians`

Introduced in R2009b

rad2nm

Convert spherical distance from radians to nautical miles

Syntax

```
nm = rad2nm(rad)
nm = rad2nm(rad, radius)
nm = rad2nm(rad, sphere)
```

Description

`nm = rad2nm(rad)` converts distances from radians to nautical miles, as measured along a great circle on a sphere with a radius of 3440.065 nm, the mean radius of the Earth.

`nm = rad2nm(rad, radius)` converts distances from radians to nautical miles, as measured along a great circle on a sphere having the specified radius.

`nm = rad2nm(rad, sphere)` converts distances from radians to nautical miles, as measured along a great circle on a sphere approximating an object in the Solar System.

Input Arguments

rad — Distance in radians

numeric array

Distance in radians, specified as a numeric array.

Data Types: `single` | `double`

radius — Radius

3440.065 (default) | numeric scalar

Radius of sphere in units of nautical miles, specified as a numeric scalar.

sphere — Sphere

'sun' | 'moon' | 'mercury' | 'venus' | 'earth' | ...

Sphere approximating an object in the Solar System, specified as one of the following values: 'sun', 'moon', 'mercury', 'venus', 'earth', 'mars', 'jupiter', 'saturn', 'uranus', 'neptune', or 'pluto'. The value of sphere is case-insensitive.

Output Arguments

nm — Distance in nautical miles

numeric array

Distance in nautical miles, returned as a numeric array.

Data Types: single | double

See Also

deg2nm | deg2rad | nm2rad | rad2deg | rad2km | rad2sm

Introduced in R2007a

rad2sm

Convert spherical distance from radians to statute miles

Syntax

```
sm = rad2sm(rad)
sm = rad2sm(rad, radius)
sm = rad2sm(rad, sphere)
```

Description

`sm = rad2sm(rad)` converts distances from radians to statute miles, as measured along a great circle on a sphere with a radius of 3958.748 sm, the mean radius of the Earth.

`sm = rad2sm(rad, radius)` converts distances from radians to statute miles, as measured along a great circle on a sphere having the specified radius.

`sm = rad2sm(rad, sphere)` converts distances from radians to statute miles, as measured along a great circle on a sphere approximating an object in the Solar System.

Examples

Convert Arc Length to Statute Miles

How long is a trip around the equator in statute miles?

```
sm = rad2sm(2*pi)
sm = 2.4874e+04
```

How about on Jupiter?

```
sm = rad2sm(2*pi, 'jupiter')
sm = 2.7283e+05
```

Input Arguments

rad — Distance in radians

numeric array

Distance in radians, specified as a numeric array.

Data Types: `single` | `double`

radius — Radius

3958.748 (default) | numeric scalar

Radius of sphere in units of statute miles, specified as a numeric scalar.

sphere — Sphere

`'sun'` | `'moon'` | `'mercury'` | `'venus'` | `'earth'` | ...

Sphere approximating an object in the Solar System, specified as one of the following values: `'sun'`, `'moon'`, `'mercury'`, `'venus'`, `'earth'`, `'mars'`, `'jupiter'`, `'saturn'`, `'uranus'`, `'neptune'`, or `'pluto'`. The value of `sphere` is case-insensitive.

Output Arguments

sm — Distance in statute miles

numeric array

Distance in statute miles, returned as a numeric array.

Data Types: `single` | `double`

See Also

`deg2rad` | `deg2sm` | `rad2deg` | `rad2km` | `rad2nm` | `sm2rad`

Introduced in R2007a

rcurve

Ellipsoidal radii of curvature

Syntax

```
r = rcurve(ellipsoid,lat)
r = rcurve('parallel',ellipsoid,lat)
r = rcurve('meridian',ellipsoid,lat)
r = rcurve('transverse',ellipsoid,lat)
r = rcurve(..., angleunits)
```

Description

`r = rcurve(ellipsoid,lat)` and `r = rcurve('parallel',ellipsoid,lat)` return the parallel radius of curvature at the latitude `lat` for a reference ellipsoid defined by `ellipsoid`, which can be a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. `r` is in units of length consistent with those used for the semimajor axis. `lat` is in 'degrees'.

`r = rcurve('meridian',ellipsoid,lat)` returns the meridional radius of curvature, which is the radius of curvature in the plane of a meridian at the latitude `lat`.

`r = rcurve('transverse',ellipsoid,lat)` returns the transverse radius of curvature, which is the radius of a curvature in a plane normal to the surface of the ellipsoid and normal to a meridian, at the latitude `lat`.

`r = rcurve(..., angleunits)` specifies the units of the input `lat`. `angleunits` can be 'degrees' or 'radians'.

Examples

The radii of curvature of the default ellipsoid at 45°, in kilometers:

```
r = rcurve('transverse',referenceEllipsoid('earth','km'),...
          45,'degrees')
```

```
r =
  6.3888e+03
```

```
r = rcurve('meridian',referenceEllipsoid('earth','km'),...
          45,'degrees')
```

```
r =
  6.3674e+03
```

```
r = rcurve('parallel',referenceEllipsoid('earth','km'),...
          45,'degrees')
```

```
r =
  4.5024e+03
```

See Also

rsphere

Introduced before R2006a

readfields

Read fields or records from fixed-format files

Syntax

```
struc = readfields(fname,fstruc)
struc = readfields(fname,fstruc,recordIDs)
struc = readfields(fname,fstruc,fieldIDs)
struc = readfields(fname,fstruc,recordIDs,mformat)
struc = readfields(fname,fstruc,recordIDs,mformat,fid)
struc = readfields(fname,fstruc,recordIDs,mformat,fid,'sparse')
```

Description

`struc = readfields(fname,fstruc)` reads all the records from a fixed format file. *fname* is a character vector containing the name of the file. If it is empty, the file is selected interactively. *fstruc* is a structure defining the format of the file. The contents of *fstruc* are described below. The result is returned in a structure.

`struc = readfields(fname,fstruc,recordIDs)` reads only the records specified in the vector *recordIDs*. For example, *recordIDs* = [1 2 3 4]. All the fields in the selected records are read.

`struc = readfields(fname,fstruc,fieldIDs)` reads only the fields specified in the cell array *fieldIDs*. For example, *fieldIDs* = {1 2 4}. The selected fields are read from all the records. *fieldIDs* can be used in place of *recordIDs* in all calling forms.

`struc = readfields(fname,fstruc,recordIDs,mformat)` opens the file with the specified machine format. *mformat* must be recognized by `fopen`.

`struc = readfields(fname,fstruc,recordIDs,mformat,fid)` reads from a file that is already open. *fid* is the file identifier returned by `fopen`. The records are read starting from the current location in the file.

`struc = readfields(fname,fstruc,recordIDs,mformat,fid,'sparse')` disables error messages when the number of elements read does not agree with the

stated format of the file. This is useful for formatted files with empty fields. Use `fid = []` for files that are not already open. This option is only compatible with reading selected records.

Background

Map data is often provided as binary or ASCII files with a fixed format. Writing your own functions to read the data into the MATLAB workspace can be difficult and time-consuming, particularly for binary files. This function allows you to read the data by simply specifying the format of the file.

Examples

Write a binary file and read it.

```
fid = fopen('testbin','wb');
for i = 1:3
    fwrite(fid,['character' num2str(i) ],'char');
    fwrite(fid,i,'int8');
    fwrite(fid,[i i],'int16');
    fwrite(fid,i,'integer*4');
    fwrite(fid,i,'real*8');
end
fclose(fid);

fs(1).length = 10;fs(1).type = 'char';fs(1).name = 'field 1';
fs(2).length = 1;fs(2).type = 'int8'; fs(2).name = 'field 2';
fs(3).length = 2;fs(3).type = 'int16';fs(3).name = 'field 3';
fs(4).length = 1;fs(4).type = 'integer*4';fs(4).name = 'field 4';
fs(5).length = 1;fs(5).type = 'float64'; fs(5).name = 'field 5';

s = readfields('testbin',fs);

s(1)
ans =
    field1: 'character1'
    field2: 1
    field3: [1 1]
    field4: 1
    field5: 1
```

Limitations

Formatted numbers must stay within the width specified for them. Files must have a size that is an integer multiple of the computed record length. This is potentially a problem for

formatted files on DOS platforms that use a carriage return/linefeed line ending everywhere except the last record. File sizes are not checked when an open file is provided.

Tips

The format of the file is described in the input argument `fstruc`. `fstruc` is a structure with one entry for every field in the file. `fstruc` has three required fields: `length`, `name`, and `type`. For fields containing binary data of the type that would be read by `fread`, `length` is the number of elements to be read, `name` is a character vector containing the field name under which the read data is stored in the output structure, and `type` is a format recognized by `fread`. Repetition modifiers such as `'40*char'` are *not* supported. Fields with empty field names are omitted from the output.

The following `fstruc` definition is for a file with a 40-character field, a field containing two integers, and a field with a single-precision floating-point number.

```
fstruc(1).length = 40;
fstruc(1).name = 'character Field'; % spaces will be suppressed
filestruc(1).type = 'char';

fstruc(2).length = 2;
fstruc(2).name = 'integer Field'; % spaces will be suppressed
fstruc(2).type = 'int16';

fstruc(3).length = 1;
fstruc(3).name = 'float Field'; % spaces will be suppressed
fstruc(3).type = 'real*4';
```

The `type` can also be a `fscanf` and `sscanf`-style format of the form `'%nX'`, where `n` is the number of characters within which the formatted data is found, and `X` is the conversion character such as `'g'` or `'d'`. For formatted fields, the `length` entry in `fstruc` is the number of elements, each of which has the width specified in the `type`. Fortran-style double-precision output such as `'0.0D00'` can be read using a `type` such as `'%nD'`, where `n` is the number of characters per element. This is an extension to the C-style formats accepted by `sscanf`. Users unfamiliar with C should note that `'d'` is preferred over `'i'` for formatted integers. MATLAB syntax follows C in interpreting `'i'` integers with leading zeros as octal. Line-ending characters in ASCII files must also be counted in the `fstruc` specification. Note that the number of line-ending characters differs across platforms.

A field specification for a formatted field with two integers each six characters wide would be of the form

```
fstruc(4).length = 2;  
fstruc(4).name = 'Elevation Units';  
fstruc(4).type = '%6d'
```

To summarize, `length` is the number of elements for binary numbers, the number of characters, and the number of elements for formatted data.

You can omit fields from all output by providing an empty character vector (`''`) for the `fstruc` name field.

See Also

[dlmread](#) | [grepfields](#) | [readmtx](#) | [spcread](#) | [textread](#)

Introduced before R2006a

readfk5

Read Fifth Fundamental Catalog of Stars

Syntax

```
struc = readfk5(filename)  
struc = readfk5(filename,struc)
```

Note readfk5 will be removed in a future release.

Description

`struc = readfk5(filename)` reads the FK5 file and returns the contents in a structure. Each star is an element in the structure, with the different data items stored in appropriately named fields.

`struc = readfk5(filename,struc)` appends the data in the file to the existing structure `struc`.

Background

The Fifth Fundamental Catalog of Stars (FK5), Parts I and II, is a compilation of data on more than 4500 stars. The catalog contains positions, errors in positions, proper motions, and characteristics such as magnitudes, spectral types, parallaxes, and radial velocities. There are also cross-references to the identities of stars in other catalogs. It was compiled by researchers at the Astronomisches Rechen-Institut in Heidelberg.

Examples

```
FK5 = readfk5('FK5.dat');  
FK5e = readfk5('FK5_ext.dat');  
whos
```

| Name | Size | Bytes | Class |
|------|--------|----------|--------------|
| FK5 | 1x1535 | 5042752 | struct array |
| FK5e | 1x3117 | 10226424 | struct array |

FK5e(1)

ans =

```
FK5: 2003
RAh: 0
RAm: 5
RAs: 1.1940
pmRA: 0.6230
DEd: 27
DEm: 40
DEs: 29.0100
pmDE: -1.1100
RAh1950: 0
RAm1950: 2
RAs1950: 26.5900
pmRA1950: 0.6210
DEd1950: 27
DEm1950: 23
DEs1950: 47.4400
pmDE1950: -1.1100
EpRA1900: 51.7200
e_RAs: 2
e_pmRA: 9
EpDE1900: 46.8200
e_DEs: 3.4000
e_pmDE: 14
Vmag: 6.4700
n_Vmag: ''
SpType: 'G5'
plx: []
RV: 12
AGK3R: '38'
SRS: ''
HD: '225292'
DM: 'BD+26 4744'
GC: '48'
```

Tips

Positions are given in terms of right ascension and declination. The Fifth Fundamental Catalog of Stars (FK5), Parts I and II data and documentation are available over the Internet by anonymous ftp.

References

See references [5] and [6] in the Bibliography located at the end of this chapter.

See Also

dms2degrees | scatterm

Introduced before R2006a

readmtx

Read matrix stored in file

Syntax

```
mtx = readmtx(fname,nrows,ncols,precision)
mtx = readmtx(fname,nrows,ncols,precision,readrows,readcols)
mtx = readmtx(fname,nrows,ncols,precision,...
readrows,readcols,mformat)
mtx = readmtx(fname,nrows,ncols,precision,...
readrows,readcols,mformat,nheadbytes)
mtx = readmtx(fname,nrows,ncols,precision,...
readrows,readcols,mformat,nheadbytes,nRowHeadBytes)
mtx = readmtx(fname,nrows,ncols,precision,...
readrows,readcols,mformat,nheadbytes,nRowHeadBytes,nRowTrailBytes)
mtx = readmtx(fname,nrows,ncols,precision,...
readrows,readcols,mformat,nheadbytes,nRowHeadBytes,...
nRowTrailBytes,nFileTrailBytes)
mtx = readmtx(fname,nrows,ncols,precision,...
readrows,readcols,mformat,nheadbytes,nRowHeadBytes,...
nRowTrailBytes,nFileTrailBytes,recordlen)
```

Description

`mtx = readmtx(fname,nrows,ncols,precision)` reads a matrix stored in a file. The file contains only a matrix of numbers with the dimensions *nrows* by *ncols* stored with the specified *precision*. Recognized *precision* values are described below.

`mtx = readmtx(fname,nrows,ncols,precision,readrows,readcols)` reads a subset of the matrix. *readrows* and *readcols* specify which rows and columns are to be read. They can be vectors containing the row or column numbers, or two-element vectors of the form [*start* *end*], which are expanded using the colon operator to *start:end*. To read just two rows or columns, without expansion by the colon operator, provide the indices as a column matrix.

`mtx = readmtx(fname, nrows, ncols, precision, ...
readrows, readcols, mformat)` specifies the machine format used to write the file. *mformat* can be any recognized by `fopen`. This option is used to automatically swap bytes for files written on platforms with a different byte ordering.

`mtx = readmtx(fname, nrows, ncols, precision, ...
readrows, readcols, mformat, nheadbytes)` skips the file header, whose length is specified in bytes.

`mtx = readmtx(fname, nrows, ncols, precision, ...
readrows, readcols, mformat, nheadbytes, nRowHeadBytes)` also skips a header that precedes every row of the matrix. The length of the header is specified in bytes.

`mtx = readmtx(fname, nrows, ncols, precision, ...
readrows, readcols, mformat, nheadbytes, nRowHeadBytes, nRowTrailBytes)` also skips a trailer that follows every row of the matrix. The length of the trailer is specified in bytes.

`mtx = readmtx(fname, nrows, ncols, precision, ...
readrows, readcols, mformat, nheadbytes, nRowHeadBytes, ...
nRowTrailBytes, nFileTrailBytes)` accounts for the length of data following the matrix. The sizes of the components of the matrix are used to compute an expected file size, which is compared to the actual file size.

`mtx = readmtx(fname, nrows, ncols, precision, ...
readrows, readcols, mformat, nheadbytes, nRowHeadBytes, ...
nRowTrailBytes, nFileTrailBytes, recordlen)` overrides the record length calculated from the precision and number of columns, and instead uses the record length given in bytes. This is used for formatted data with extra spaces or line breaks in the matrix.

Background

Map data is often provided as binary or ASCII files with a fixed format. Writing your own functions to read the data into the MATLAB workspace can be difficult and time-consuming, particularly for binary files. This function allows you to read the data by simply specifying the format of the file.

Examples

Write and read a binary matrix file:

```
fid = fopen('binmat','w');
fwrite(fid,1:100,'int16');
fclose(fid);
mtx = readmtx('binmat',10,10,'int16')
```

```
mtx =
    1     2     3     4     5     6     7     8     9    10
   11    12    13    14    15    16    17    18    19    20
   21    22    23    24    25    26    27    28    29    30
   31    32    33    34    35    36    37    38    39    40
   41    42    43    44    45    46    47    48    49    50
   51    52    53    54    55    56    57    58    59    60
   61    62    63    64    65    66    67    68    69    70
   71    72    73    74    75    76    77    78    79    80
   81    82    83    84    85    86    87    88    89    90
   91    92    93    94    95    96    97    98    99   100
```

```
mtx = readmtx('binmat',10,10,'int16',[2 5],3:2:9)
```

```
mtx =
   13    15    17    19
   23    25    27    29
   33    35    37    39
   43    45    47    49
```

Limitations

Every row of the matrix must have the same number of elements.

Tips

This function reads files that have a general format consisting of a header, a matrix, and a trailer. Each row of the matrix can have a certain number of bytes of extraneous information preceding or following the matrix data.

Both binary and formatted data files can be read. If the file is binary, the precision argument is a format recognized by `fread`. Repetition modifiers such as `'40*char'` are

not supported. If the file is formatted, precision is a `fscanf` and `sscanf`-style format of the form `'%nX'`, where `n` is the number of characters within which the formatted data is found, and `X` is the conversion character such as `'g'` or `'d'`. Fortran-style double-precision output such as `'0.0D00'` can be read using a precision such as `'%nD'`, where `n` is the number of characters per element. This is an extension to the C-style format `s` accepted by `sscanf`. Users unfamiliar with C should note that `'%d'` is preferred over `'%i'` for formatted integers. MATLAB syntax follows C in interpreting `'%i'` integers with leading zeros as octal. Formatted files with line endings need to provide the number of trailing bytes per row, which can be 1 for platforms with carriage returns *or* linefeed (Macintosh, UNIX), or 2 for platforms with carriage returns *and* linefeeds (DOS).

See Also

`dlmread` | `readfields` | `spcread` | `textread`

Introduced before R2006a

reckon

Point at specified azimuth, range on sphere or ellipsoid

Syntax

```
[latout,lonout] = reckon(lat,lon,arclen,az)
[latout,lonout] = reckon(lat,lon,arclen,az,units)
[latout,lonout] = reckon(lat,lon,arclen,az,ellipsoid)
[latout,lonout] = reckon(lat,lon,arclen,az,ellipsoid,units)
[latout,lonout] = reckon(track,...)
```

Description

[latout,lonout] = reckon(lat,lon,arclen,az), for scalar inputs, calculates a position (latout,lonout) at a given range, arclen, and azimuth, az, along a great circle from a starting point defined by lat and lon. lat and lon are in degrees. arclen must be expressed as degrees of arc on a sphere, and equals the length of a great circle arc connecting the point (lat, lon) to the point (latout, lonout). az, also in degrees, is measured clockwise from north. reckon calculates multiple positions when given four arrays of matching size. When given a combination of scalar and array inputs, the scalar inputs are automatically expanded to match the size of the arrays.

[latout,lonout] = reckon(lat,lon,arclen,az,units), where units is either 'degrees' or 'radians', specifies the units of the inputs and outputs, including arclen. The default value is 'degrees'.

[latout,lonout] = reckon(lat,lon,arclen,az,ellipsoid) calculates positions along a geodesic on an ellipsoid, as specified by ellipsoid. ellipsoid is a referenceSphere, referenceEllipsoid, or oblateSpheroid object, or a vector of the form [semimajor_axis eccentricity]. The range, arclen, must be expressed same unit of length as the semimajor axis of the ellipsoid.

[latout,lonout] = reckon(lat,lon,arclen,az,ellipsoid,units) calculates positions on the specified ellipsoid with lat, lon, az, latout, and lonout in the specified angle units.

[latout,lonout] = reckon(track,...) calculates positions on great circles (or geodesics) if track is 'gc' and along rhumb lines if track is 'rh'. The default value is 'gc'.

Examples

Find the coordinates of the point 600 nautical miles northwest of London, UK (51.5°N,0°) in a great circle sense:

```
% Convert nm distance to degrees.
dist = nm2deg(600)
dist =
    9.9933
```

```
% Northwest is 315 degrees.
pt1 = reckon(51.5,0,dist,315)
pt1 =
    57.8999  -13.3507
```

Now, determine where a plane from London traveling on a constant northwesterly course for 600 nautical miles would end up:

```
pt2 = reckon('rh',51.5,0,dist,315)

pt2 =
    58.5663  -12.3699
```

How far apart are the points above (distance in great circle sense)?

```
separation = distance('gc',pt1,pt2)

separation =
    0.8430
```

```
% Convert answer to nautical miles.
nmsep = deg2nm(separation)
nmsep =
    50.6156
```

Over 50 nautical miles separate the two points.

See Also

azimuth | distance | dreckon | km2deg | track | track1 | track2

Introduced before R2006a

map.geodesy.RectifyingLatitudeConverter

Convert between geodetic and rectifying latitudes

Description

A `RectifyingLatitudeConverter` object provides conversion methods between geodetic and rectifying latitudes for an ellipsoid with a given third flattening.

The rectifying latitude maps an ellipsoid (oblate spheroid) to a sphere while preserving the distances along the meridians. Rectifying latitudes are used when implementing map projections, such as Equidistant Cylindrical, that preserve such distances.

Creation

Syntax

```
converter = map.geodesy.RectifyingLatitudeConverter  
converter = map.geodesy.RectifyingLatitudeConverter(spheroid)
```

Description

`converter = map.geodesy.RectifyingLatitudeConverter` returns a `RectifyingLatitudeConverter` object for a sphere and sets the `ThirdFlattening` property to 0.

`converter = map.geodesy.RectifyingLatitudeConverter(spheroid)` returns a rectifying latitude converter object and sets the `ThirdFlattening` property to match the specified spheroid object.

Input Arguments

spheroid — Reference spheroid

referenceEllipsoid | oblateSpheroid | referenceSphere

Reference spheroid, specified as a `referenceEllipsoid`, `oblateSpheroid`, or `referenceSphere` object. To create a spheroid object, use the creation function specific to the object, or the `wgs84Ellipsoid` function.

Example: `spheroid = referenceEllipsoid('GRS 80');`

Properties

ThirdFlattening — Third flattening of an ellipsoid

numeric scalar

Third flattening of an ellipsoid, specified as a numeric scalar. `ThirdFlattening` is in the interval $[0, ecc2n(0.5)]$, or approximately $[0, 0.071797]$. (Flatter spheroids are possible in theory, but do not occur in practice and are not supported.)

Data Types: `double`

Object Functions

`forward` Convert geodetic latitude to authalic, conformal, isometric, or rectifying latitude

`inverse` Convert authalic, conformal, isometric, or rectifying latitude to geodetic latitude

Examples

Create a Rectifying Latitude Converter Object and Set Property

```
grs80 = referenceEllipsoid('GRS 80');  
  
conv1 = map.geodesy.RectifyingLatitudeConverter;  
conv1.ThirdFlattening = grs80.ThirdFlattening  
  
conv1 =
```

RectifyingLatitudeConverter with properties:


```
ThirdFlattening: 0.0017
```

Create a Rectifying Latitude Converter Object, Specifying Spheroid

```
grs80 = referenceEllipsoid('GRS 80');  
conv2 = map.geodesy.RectifyingLatitudeConverter(grs80)  
conv2 =
```

```
RectifyingLatitudeConverter with properties:
```

```
ThirdFlattening: 0.0017
```

See Also

Functions

[geocentricLatitude](#) | [parametricLatitude](#)

Objects

[AuthalicLatitudeConverter](#) | [ConformalLatitudeConverter](#) |
[IsometricLatitudeConverter](#)

Introduced in R2013a

reducem

Reduce density of points in vector data

Syntax

```
[latout,lonout] = reducem(latin,lonin)
[latout,lonout] = reducem(latin,lonin,tol)
[latout,lonout,cerr] = reducem(...)
[latout,lonout,cerr,tol] = reducem(...)
```

Description

`[latout,lonout] = reducem(latin,lonin)` reduces the number of points in vector map data. In this case the tolerance is computed automatically.

`[latout,lonout] = reducem(latin,lonin,tol)` uses the provided tolerance. The units of the tolerance are degrees of arc on the surface of a sphere.

`[latout,lonout,cerr] = reducem(...)` in addition returns a measure of the error introduced by the simplification. The output `cerr` is the difference in the arc length of the original and reduced data, normalized by the original length.

`[latout,lonout,cerr,tol] = reducem(...)` also returns the tolerance used in the reduction, which is useful when the tolerance is computed automatically.

Examples

Compare the original and reduced outlines of the District of Columbia from the `usastatehi` state outline data:

```
dc = shaperead('usastatehi',...
    'UseGeoCoords', true,...
    'Selector',{@(name) ...
        strcmpi(name,'district of columbia'), 'Name'});
lat = extractfield(dc, 'Lat');
```

```


lon = extractfield(dc, 'Lon');
[latreduced, lonreduced] = reducem(lat, lon);

lonlim = dc.BoundingBox(:,1)' + [-0.02 0.02];
latlim = dc.BoundingBox(:,2)' + [-0.02 0.02];

subplot(1,2,1)
usamap(latlim, lonlim); axis off
geoshow(lat, lon,...
        'DisplayType', 'polygon', 'FaceColor', 'blue')

subplot(1,2,2)
usamap(latlim, lonlim); axis off
geoshow(latreduced, lonreduced,...
        'DisplayType', 'polygon', 'FaceColor', 'yellow')

```



Tips

Vector data is reduced using the Douglas-Peucker line simplification algorithm. This method recursively subdivides a polygon until a run of points can be replaced by a straight line segment, with no point in that run deviating from the straight line by more than the tolerance. The distances used to decide on which runs of points to eliminate are computed in a Plate Carrée projection.

Reduced geographic data might not always be appropriate for display. If all intermediate points in a data set are reduced, then lines appearing straight in one projection are incorrectly displayed as straight lines in others.

See Also

`interp` | `resize`

Introduced before R2006a

referenceEllipsoid

Reference ellipsoid

Description

A `referenceEllipsoid` object encapsulates a reference ellipsoid, modeled as an oblate spheroid with three additional properties: name, unit of length of the semi-major and semi-minor axes, and a numerical EPSG code.

Creation

You can create a general `referenceEllipsoid` object with the `referenceEllipsoid` function described here. You can also create a `referenceEllipsoid` with properties specific to the World Geodetic System 1984 reference ellipsoid using the `wgs84Ellipsoid` function.

```
E = referenceEllipsoid
E = referenceEllipsoid(name)
E = referenceEllipsoid(code)
E = referenceEllipsoid(name, lengthUnit)
E = referenceEllipsoid(code, lengthUnit)
```

Description

`E = referenceEllipsoid` creates a `referenceEllipsoid` object that represents the unit sphere.

`E = referenceEllipsoid(name)` creates a `referenceEllipsoid` object corresponding to `name`. `name` is case-insensitive. The values of the `SemimajorAxis` and `SemiminorAxis` properties are in meters.

`E = referenceEllipsoid(code)` creates a `referenceEllipsoid` object corresponding to the numerical EPSG code, `code`. All of the nearly 60 codes in the EPSG ellipsoid table are supported. The unit of length used for the `SemimajorAxis` and `SemiminorAxis` properties depends on the ellipsoid selected, and is indicated in the property `LengthUnit`.

`E = referenceEllipsoid(name,lengthUnit)` and

`E = referenceEllipsoid(code,lengthUnit)` create a `referenceEllipsoid` object with the `SemimajorAxis` and `SemiminorAxis` properties in the specified unit of length, `LengthUnit`. The unit of length can be any length unit supported by the `validateLengthUnit` function.

Properties

Code — Numerical EPSG code

`[]` (default) | integer between 7000 and 8000

Numerical EPSG code, specified as an empty vector or an integer between 7000 and 8000, although not all integers in this range are valid numerical EPSG codes. The code indicates a row in the EPSG ellipsoid table corresponding to the `referenceEllipsoid`.

When the reference ellipsoid represents the unit sphere, `Code` is an empty vector, `[]`.

Example: 7030

Data Types: double

Name — Name of the reference ellipsoid

`'Unit Sphere'` (default) | character vector

Name of the reference ellipsoid, specified as a character vector. Supported names appear in the table “Names of EPSG Ellipsoids” on page 1-1194. Both the short version and the long version of the ellipsoid name are acceptable as values of the `Name` property.

When the reference ellipsoid represents the unit sphere, `Name` is the character vector `'Unit Sphere'`.

Example: `'World Geodetic System 1984'`

Data Types: char

LengthUnit — Unit of length for the ellipsoid axes

`''` (default) | character vector

Unit of length for the ellipsoid axes, specified as a character vector. The character vector can be empty, or it can be any unit of length accepted by the `validateLengthUnit` function.

When the reference ellipsoid represents the unit sphere, `LengthUnit` is the empty character vector `''`.

Example: `'km'`

Data Types: `char`

SemimajorAxis — Equatorial radius of ellipsoid

1 (default) | positive, finite scalar

Equatorial radius of ellipsoid, specified as a positive, finite scalar. The `SemimajorAxis` property is expressed in units of length specified by `LengthUnit`.

When the `SemimajorAxis` property is changed, the `SemiminorAxis` property scales as needed to preserve the shape of the ellipsoid and the values of shape-related properties including `InverseFlattening` and `Eccentricity`. The only way to change the `SemimajorAxis` property is to set it directly, using dot notation.

Example: `6378137`

Data Types: `double`

SemiminorAxis — Distance from center of ellipsoid to pole

1 (default) | nonnegative, finite scalar

Distance from center of ellipsoid to pole, specified as a nonnegative, finite scalar. The value of `SemiminorAxis` is always less than or equal to `SemimajorAxis`, and is expressed in units of length specified by `LengthUnit`.

When the `SemiminorAxis` property is changed, the `SemimajorAxis` property remains unchanged, but the shape of the ellipsoid changes, which is reflected in changes in the values of `InverseFlattening`, `Eccentricity`, and other shape-related properties.

Example: `6356752`

Data Types: `double`

InverseFlattening — Reciprocal of flattening

Inf (default) | positive scalar in the range [1, Inf]

Reciprocal of flattening, specified as positive scalar in the range [1, Inf].

The value of inverse flattening, $1/f$, is calculated using `SemimajorAxis` value a and `SemiminorAxis` value b according to $1/f = a/(a-b)$. A value $1/f$ of `Inf` designates a perfect sphere. As $1/f$ approaches 1, the reference ellipsoid approaches a flattened disk.

When the `InverseFlattening` property is changed, other shape-related properties update, including `Eccentricity`. The `SemimajorAxis` property remains unchanged, but the value of `SemiminorAxis` adjusts to reflect the new shape.

Example: 300

Data Types: double

Eccentricity — First eccentricity of ellipsoid

0 (default) | nonnegative scalar in the range [0, 1]

First eccentricity of the ellipsoid, specified as nonnegative scalar in the range [0, 1].

The value of eccentricity, ecc , is calculated using `SemimajorAxis` value a and `SemiminorAxis` value b according to $ecc = \sqrt{(a^2 - b^2)}/a$. A value ecc of 0 designates a perfect sphere.

When the `Eccentricity` property is changed, other shape-related properties update, including `InverseFlattening`. The `SemimajorAxis` property remains unchanged, but the value of `SemiminorAxis` adjusts to reflect the new shape.

Example: 0.08

Data Types: double

Flattening — Flattening of ellipsoid

nonnegative scalar in the range [0, 1]

This property is read-only.

Flattening of the ellipsoid, specified as nonnegative scalar in the range [0, 1].

The value of flattening, f , is calculated using `SemimajorAxis` value a and `SemiminorAxis` value b according to $f = (a-b)/a$.

Data Types: double

ThirdFlattening — Third flattening of ellipsoid

nonnegative scalar in the range [0, 1]

This property is read-only.

Third flattening of the ellipsoid, specified as nonnegative scalar in the range [0, 1].

The value of the third flattening, n , is calculated using SemimajorAxis value a and SemiminorAxis value b according to $n = (a-b)/(a+b)$.

Data Types: double

MeanRadius — Mean radius of the ellipsoid

positive, finite scalar

This property is read-only.

Mean radius of the ellipsoid, specified as positive, finite scalar. The MeanRadius property is expressed in units of length specified by LengthUnit.

The mean radius of the ellipsoid, r , is calculated using SemimajorAxis value a and SemiminorAxis value b according to $r = (2a+b)/3$.

Data Types: double

SurfaceArea — Surface area of the ellipsoid

positive, finite scalar

This property is read-only.

Surface area of the ellipsoid, specified as positive, finite scalar. The SurfaceArea property is expressed in units of area consistent the unit of length specified by the LengthUnit property.

Data Types: double

Volume — Volume of the ellipsoid

positive, finite scalar

This property is read-only.

Volume of the ellipsoid, specified as positive, finite scalar. The Volume property is expressed in units of volume consistent with the unit of length specified by the LengthUnit property.

Data Types: double

Examples

Construct GRS80 Reference Ellipsoide

Create a reference ellipsoid object by specifying the name of the ellipsoid.

```
e = referenceEllipsoid('Geodetic Reference System 1980')
```

```
e =  
referenceEllipsoid with defining properties:
```

```
          Code: 7019  
          Name: 'Geodetic Reference System 1980'  
          LengthUnit: 'meter'  
          SemimajorAxis: 6378137  
          SemiminorAxis: 6356752.31414036  
          InverseFlattening: 298.257222101  
          Eccentricity: 0.0818191910428158
```

```
and additional properties:
```

```
          Flattening  
          ThirdFlattening  
          MeanRadius  
          SurfaceArea  
          Volume
```

Create the same reference ellipsoid object by specifying the EPSG code 7019.

```
e = referenceEllipsoid(7019)
```

```
e =  
referenceEllipsoid with defining properties:
```

```
          Code: 7019  
          Name: 'GRS 1980'  
          LengthUnit: 'meter'  
          SemimajorAxis: 6378137  
          SemiminorAxis: 6356752.31414036  
          InverseFlattening: 298.257222101  
          Eccentricity: 0.0818191910428158
```

```
and additional properties:
```

```
          Flattening  
          ThirdFlattening
```

```

MeanRadius
SurfaceArea
Volume

```

Create a reference ellipsoid object, specifying the units. For length unit, you can specify any unit of length accepted by the `validateLengthUnit` function.

```
e = referenceEllipsoid('GRS80', 'km')
```

```
e =
referenceEllipsoid with defining properties:
```

```

                Code: 7019
                Name: 'Geodetic Reference System 1980'
                LengthUnit: 'kilometer'
                SemimajorAxis: 6378.137
                SemiminorAxis: 6356.75231414036
                InverseFlattening: 298.257222101
                Eccentricity: 0.0818191910428158

```

```
and additional properties:
```

```

Flattening
ThirdFlattening
MeanRadius
SurfaceArea
Volume

```

Create a reference ellipsoid, specifying the `GeoTIFFCodes.Ellipsoid` field from a file.

```
info = geotiffinfo('boston.tif');
e = referenceEllipsoid(info.GeoTIFFCodes.Ellipsoid)
```

```
e =
referenceEllipsoid with defining properties:
```

```

                Code: 7019
                Name: 'GRS 1980'
                LengthUnit: 'meter'
                SemimajorAxis: 6378137
                SemiminorAxis: 6356752.31414036
                InverseFlattening: 298.257222101
                Eccentricity: 0.0818191910428158

```

and additional properties:

```
Flattening  
ThirdFlattening  
MeanRadius  
SurfaceArea  
Volume
```

Definitions

Names of EPSG Ellipsoids

All of the nearly 60 codes in the EPSG ellipsoid table are supported. A subset of these ellipsoids can be created by specifying their name. The short and long names of these ellipsoids, along with their corresponding code, appear in the table.

| EPSG Code | Short Name | Long Name |
|-----------|-----------------|----------------------------------|
| — | 'unitsphere' | 'Unit Sphere' |
| 7019 | 'grs80' | 'Geodetic Reference System 1980' |
| 7030 | 'wgs84' | 'World Geodetic System 1984' |
| 7015 | 'everest' | 'Everest 1830' |
| 7004 | 'bessel' | 'Bessel 1841' |
| 7001 | 'airy1830' | 'Airy 1830' |
| 7002 | 'airy1849' | 'Airy Modified 1849' |
| 7008 | 'clarke66' | 'Clarke 1866' |
| 7012 | 'clarke80' | 'Clarke 1880' |
| 7022 | 'international' | 'International 1924' |
| 7024 | 'krasovsky' | 'Krasovsky 1940' |

| EPSG Code | Short Name | Long Name |
|-----------|------------|---|
| 7043 | 'wgs72' | 'World Geodetic System 1972' |
| — | 'wgs60' | 'World Geodetic System 1960' |
| — | 'iau65' | 'International Astronomical Union 1965' |
| — | 'wgs66' | 'World Geodetic System 1966' |
| — | 'iau68' | 'International Astronomical Union 1968' |
| 7030 | 'earth' | 'World Geodetic System 1984' |
| — | 'sun' | 'Sun' |
| — | 'moon' | 'Moon' |
| — | 'mercury' | 'Mercury' |
| — | 'venus' | 'Venus' |
| — | 'mars' | 'Mars' |
| — | 'jupiter' | 'Jupiter' |
| — | 'saturn' | 'Saturn' |
| — | 'uranus' | 'Uranus' |
| — | 'neptune' | 'Neptune' |
| — | 'pluto' | 'Pluto' |

Tips

- When you define an ellipsoid in terms of semimajor and semiminor axes (rather than semimajor axis and inverse flattening, or semimajor axis and eccentricity), a small loss of precision in the last few digits of Flattening, Eccentricity, and

`ThirdFlattening` may occur. This is unavoidable, but does not affect the results of practical computation.

See Also

`oblateSpheroid` | `referenceSphere` | `validateLengthUnit` | `wgs84Ellipsoid`

Introduced in R2012a

referenceSphere

Reference ellipsoid

Description

A `referenceSphere` object represents a sphere with a specific name and radius that you can use in map projections and other geodetic operations.

Creation

```
S = referenceSphere  
S = referenceSphere(name)  
S = referenceSphere(name, lengthUnit)
```

Description

`S = referenceSphere` creates a `referenceSphere` object that represents the unit sphere.

`S = referenceSphere(name)` creates a `referenceSphere` object corresponding to the specified spherical body given by `name`. The radius of the reference sphere is in meters.

`S = referenceSphere(name, lengthUnit)` creates a `referenceSphere` object with radius in the specified unit of length, `LengthUnit`. The unit of length can be any length unit supported by the `validateLengthUnit` function.

Properties

Name — Name of reference sphere

'Unit Sphere' (default) | character vector | string scalar

Name of the reference sphere, specified as a string scalar or character vector. Supported names of spherical bodies are: 'earth', 'sun', 'moon', 'mercury', 'venus',

'mars', 'jupiter', 'saturn', 'uranus', 'neptune', and 'pluto'. When the reference sphere represents the unit sphere, Name is the character vector 'Unit Sphere'.

Example: 'Sun'

Data Types: char | string

LengthUnit — Unit of length of the radius

' ' (default) | character vector | string scalar

Unit of length of the radius, specified as a string scalar or character vector. You can specify any unit of length accepted by the `validateLengthUnit` function. When the reference ellipsoid represents the unit sphere, LengthUnit is the empty character vector ''.

Example: 'km'

Data Types: char | string

Radius — Radius of the sphere

positive, finite scalar

Radius of the sphere, specified as positive, finite scalar.

Data Types: double

SemimajorAxis — Equatorial radius of the sphere

1 (default) | positive, finite scalar

This property is read-only.

Equatorial radius of the sphere, specified as a positive, finite scalar. The value of SemimajorAxis is equal to the value of Radius.

Data Types: double

SeminorAxis — Distance from center of sphere to pole

1 (default) | positive, finite scalar

This property is read-only.

Distance from center of sphere to pole, specified as a positive, finite scalar. The value of SemiminorAxis is equal to the value of Radius.

Data Types: double

InverseFlattening — Reciprocal of flattening

Inf (default)

This property is read-only.

Reciprocal of flattening, specified as the value Inf.

Data Types: double

Eccentricity — First eccentricity of sphere

0 (default)

This property is read-only.

First eccentricity of the sphere, specified as the value 0.

Data Types: double

Flattening — Flattening of sphere

0 (default)

This property is read-only.

Flattening of the sphere, specified as the value 0.

Data Types: double

ThirdFlattening — Third flattening of sphere

0 (default)

This property is read-only.

Third flattening of the sphere, specified as the value 0.

Data Types: double

MeanRadius — Mean radius of the sphere

positive, finite scalar

This property is read-only.

Mean radius of the sphere, specified as positive, finite scalar. The value of MeanRadius is equal to the value of Radius.

Data Types: double

SurfaceArea — Surface area of the sphere

positive, finite scalar

This property is read-only.

Surface area of the sphere, specified as positive, finite scalar.

The `SurfaceArea` property is expressed in units of area consistent with the unit of length specified by the `LengthUnit` property.

Data Types: double

Volume — Volume of the sphere

positive, finite scalar

This property is read-only.

Volume of the sphere, specified as positive, finite scalar.

The `Volume` property is expressed in units of volume consistent with the unit of length specified by the `LengthUnit` property.

Data Types: double

Examples

Create a Model of Earth in Kilometers

Construct a reference sphere that models the Earth as a sphere with a radius of 6371000 meters. Note that the unit of length is meters.

```
s = referenceSphere('Earth')
```

```
s =
```

```
referenceSphere with defining properties:
```

```
    Name: 'Earth'  
 LengthUnit: 'meter'  
    Radius: 6371000
```

```
and additional properties:
```

```
SemimajorAxis  
SemiminorAxis  
InverseFlattening  
Eccentricity  
Flattening  
ThirdFlattening  
MeanRadius  
SurfaceArea  
Volume
```

Switch the unit of length in the reference sphere to kilometers.

```
s.LengthUnit = 'kilometer'
```

```
s =
```

referenceSphere with defining properties:

```
    Name: 'Earth'  
    LengthUnit: 'kilometer'  
    Radius: 6371
```

and additional properties:

```
SemimajorAxis  
SemiminorAxis  
InverseFlattening  
Eccentricity  
Flattening  
ThirdFlattening  
MeanRadius  
SurfaceArea  
Volume
```

Determine the surface area of the sphere in square kilometers.

```
s.SurfaceArea
```

```
ans =
```

```
5.1006e+08
```

Find the volume of the sphere in cubic kilometers.

```
s.Volume
```

```
ans =
```

```
1.0832e+12
```

See Also

[oblateSpheroid](#) | [referenceEllipsoid](#) | [validateLengthUnit](#)

Introduced in R2012a

refine

Refine search of WMS layers

Syntax

```
refined = refine(layers,querystr)
refined = refine( __ ,Name,Value,...)
```

Description

`refined = refine(layers,querystr)` searches fields of Web map service layers, `layers`, for a partial match with the string or character vector in `querystr`. By default, `refine` searches the `Layer` or `LayerName` properties but you can include other fields in the search using the `SearchFields` parameter.

`refined = refine(__ ,Name,Value,...)` modifies the search based on the values of the named parameters.

Examples

Refine Search of Temperature Layers

First find layers in the WMS database that contain temperature information.

```
temperature = wmsfind('temperature');
```

Refine the search of temperature layers to find only those layers that contain annual temperature information.

```
annual = refine(temperature,'annual');
```

Refine the search of temperature layers to find layers containing only sea surface temperatures.

```
sst = refine(temperature,'sea surface');
```

Refine the search of sea surface temperature layers to include only layers that include annual information.

```
annual_and_sst = refine(sst, 'annual');  
annual_or_sst = [sst;annual];
```

Input Arguments

layers — Layers to search

array of `WMSLayer` objects

Layers to search, specified as an array of `WMSLayer` objects.

querystr — Characters to search for in `WMSLayer` object fields

character vector | string

Characters to search for in `WMSLayer` object fields, specified as a string or character vector. `querystr` can contain the asterisk wildcard character (*).

Example: 'temperature'

Data Types: char | string

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1,Value1,...,NameN,ValueN`.

Example: 'IgnoreCase', false

SearchFields — Fields to search in the `WMSLayer` objects

'layer' (default) | 'server' | 'layertitle' | 'layername' | 'servertitle' |
'serverurl' | 'any' | 'abstract'

Fields to search in the `WMSLayer` objects, specified as a string, string array, character vector, or cell array of character vectors. The function searches the values of the specified fields in the `WMSLayer` objects for a partial or exact match with `querystr`. Multiple options may be included in a string array or cell array of character vectors.

The table lists valid values of searchFields.

| Field | Behavior |
|---------------|--|
| 'layer' | Search both the LayerTitle and the LayerName fields. |
| 'layername' | Search the LayerName field in the WMSLayer objects. The layer name is an abbreviated form of the LayerTitle field and is the keyword the server uses to retrieve the layer. |
| 'layertitle' | Search the LayerTitle field in the WMSLayer objects. The layer title includes descriptive information about a layer and facilitates understanding the meaning of the raster values of the layer. |
| 'server' | Search the ServerURL in the WMSLayer objects. The server URL and layer information facilitate the reading of raster layers by the function wmsread. |
| 'servertitle' | Search the ServerTitle field in the WMSLayer objects. A server title includes descriptive information about the server. |
| 'serverurl' | Search the ServerURL in the WMSLayer objects. The server URL and layer information facilitate the reading of raster layers by the function wmsread. |
| 'abstract' | Search the abstract field in the WMSLayer objects. |
| 'any' | Search all fields. |

Data Types: char | string

MatchType — Strictness of match

'partial' (default) | 'exact'

Strictness of match, specified as the string or character vector 'partial' or 'exact'. If 'MatchType' is 'exact' and querystr is '*', a match occurs when the search field matches the character '*'.

Data Types: char | string

IgnoreCase — Ignore case when comparing field values to querystr

true (default) | false

Ignore case when comparing field values to `querystr`, specified as the logical value `true` or `false`.

Data Types: `logical`

Output Arguments

refined — Refined layers

array of `WMSLayer` objects

Refined layers, specified as an array of `WMSLayer` objects. Each layer in the array has a searched field that matches the text query, `querystr`.

See Also

`refineLimits` | `wmsfind`

Introduced in R2009b

refineLimits

Refine search of WMS layers based on geographic limits

Syntax

```
refined = refineLimits(layers,Name,Value,...)
```

Description

`refined = refineLimits(layers,Name,Value,...)` searches for elements of Web map service layers, `layers`, that match specific latitude or longitude limits. The results include a given layer only if the quadrangle specified by the optional `'Latlim'` and `'Lonlim'` parameters fully contains the boundary quadrangle, as defined by the `Latlim` and `Lonlim` properties. Partial overlap does not result in a match. All angles are in units of degrees.

Examples

Find Layers Containing Global Elevation Data

Find layers containing global elevation data.

```
elevation = wmsfind('elevation');  
latlim = [-90, 90];  
lonlim = [-180, 180];  
globalElevation = ...  
    refineLimits(elevation,'Latlim', latlim, 'Lonlim', lonlim);
```

Print out the server titles from the unique servers.

```
globalElevation.serverTitles'
```

```
ans =
```

```
    'Ceoware2 WMS'
```

```
'CubeSERV WMS'  
'CubeSERV Demo WMS'  
'deegree wms'  
'NASA Earth Observations (NEO) WMS'  
'JPL Planetary Map Service'  
'LMMP Tiled Web Map Service'  
'MicroImages TNTserver 7.3'  
'CubeSERV WMS'  
'ORNL DAAC WMS Server'  
'WMS GEOBASE / GEOBASE WMS'  
'NASA WorldWind WMS'  
'World Map'  
'World Map'  
'CubeSERV WMS'
```

Input Arguments

layers — Layers to search

array of `WMSLayer` object

Layers to search, specified as an array of `WMSLayer` objects.

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

Example: `'Latlim', [0 90]`

Latlim — Latitudinal limits to search

two-element vector

Latitudinal limits to search, specified as a two-element vector. `Latlim` is in the form `[southern_limit northern_limit]` or a scalar value representing the latitude of a single point.

Example: `[-90, 90]`

Lonlim — Longitudinal limits to search

numeric scalar | two-element numeric vector

Longitudinal limits to search, specified as a numeric scalar or two-element numeric vector. `Lonlim` is in the form `[western_limit eastern_limit]` or a scalar value representing the longitude of a single point.

Example: `[-180, 180]`

Output Arguments

refined — Refined layers

array of `WMSLayer` objects

Refined layers, specified as an array of `WMSLayer` objects. Each layer in the array has a boundary quadrangle that is fully contained in the quadrangle defined by the specified `'Latlim'` and `'Lonlim'` parameters.

Tips

- The default value of `[]` for either `'Latlim'` or `'Lonlim'` implies that all layers match the criteria. For example, if you specify the following, then the results include all the layers that cover the northern hemisphere.

```
refineLimits(layer,'Latlim', [0 90], 'Lonlim', [])
```

See Also

`refine` | `wmsfind`

Introduced in R2009b

refmat2vec

Convert referencing matrix to referencing vector

Note `refmat2vec` will be removed in a future release. Use `refmatToGeoRasterReference` instead, which will construct a geographic raster reference object.

Syntax

```
refvec = refmat2vec(R,s)
```

Description

`refvec = refmat2vec(R,s)` converts a referencing matrix, `R`, to the three-element referencing vector `refvec`. `R` is a 3-by-2 referencing matrix defining a two-dimensional affine transformation from pixel coordinates to spatial coordinates. `s` is the size of the array (data grid) that is being referenced. `refvec` is a 1-by-3 referencing vector having elements [cells/degree north-latitude west-longitude] with latitude and longitude limits specified in degrees.

Examples

```
% Verify the conversion of the geoid referencing vector to a  
% referencing matrix.  
load geoid;  
R = refvec2mat(geoidlegend, size(geoid));  
V = refmat2vec(R, size(geoid));
```

See Also

`makerefmat` | `refmatToGeoRasterReference`

Introduced before R2006a

refvec2mat

Convert referencing vector to referencing matrix

Note `refvec2mat` will be removed in a future release. Use `refvecToGeoRasterReference` instead, which will construct a geographic raster reference object.

Syntax

```
R = refvec2mat(refvec,s)
```

Description

`R = refvec2mat(refvec,s)` converts a referencing vector, `refvec`, to the referencing matrix `R`. `refvec` is a 1-by-3 referencing vector having elements [`cells/degree north-latitude west-longitude`] with latitude and longitude limits specified in degrees. `s` is the size of the array (data grid) that is being referenced. `R` is a 3-by-2 referencing matrix defining a two-dimensional affine transformation from pixel coordinates to spatial coordinates.

Examples

```
% Convert the geoid referencing vector to a referencing matrix
load geoid;
R = refvec2mat(geoidlegend, size(geoid));
```

See Also

`makerefmat` | `refvecToGeoRasterReference`

Introduced before R2006a

refmatToGeoRasterReference

Referencing matrix to geographic raster reference object

Syntax

```
R = refmatToGeoRasterReference(refmat,rasterSize)
R = refmatToGeoRasterReference( ____,rasterInterpretation)
R = refmatToGeoRasterReference( ____,funcName,varName,argIndex)
R = refmatToGeoRasterReference(Rin,rasterSize, ____)
```

Description

`R = refmatToGeoRasterReference(refmat,rasterSize)` constructs a cell-oriented geographic raster reference object, `R`, from a referencing matrix, `refmat`, and a size vector, `rasterSize`.

`R = refmatToGeoRasterReference(____,rasterInterpretation)` uses the `rasterInterpretation` input to determine which type of geographic raster reference object to construct. The `rasterInterpretation` input indicates basic geometric nature of the raster, and can equal either 'cells' or 'postings'.

`R = refmatToGeoRasterReference(____,funcName,varName,argIndex)` uses up to three optional arguments to provide additional information. This information is used to construct error messages if either the `refmat` or `rasterSize` inputs turn out to be invalid. Thus, you can use `refmatToGeoRasterReference` for both validating and converting a referencing matrix. The optional inputs work just like their counterparts in the MATLAB function `validateattributes`.

`R = refmatToGeoRasterReference(Rin,rasterSize, ____)` verifies that size of the geographic raster reference object, `Rin` is consistent with the size specified by `rasterSize`, and then copies `Rin` to `R`. `refmatToGeoRasterReference` gets size information from the `Rin.RasterSize` property.

Input Arguments

refmat

Any valid referencing matrix. The matrix must lead to valid latitude and longitude limits when combined with `rasterSize`, and the matrix columns and rows must be aligned with meridians and parallels, respectively.

rasterSize

Size vector [M N ...] specifying the number of rows (M) and columns (N) in the raster or image to be associated with the geographic raster reference object, R. For convenience, `rasterSize` may be a row vector with more than two elements. This flexibility allows you to specify the size in the following way:

```
R = refmatToGeoRasterReference(refmat, size(RGB))
```

where RGB is *M*-by-*N*-by-3. However, in such cases, only the first two elements of the size vector are actually used. The higher (non-spatial) dimensions are ignored.

rasterInterpretation

Basic geometric nature of the raster, specified as either 'cells' or 'postings'.

funcName

Name used in the formatted error message to identify the function checking the input, specified as a character vector.

varName

Name used in the formatted error message to identify the referencing matrix, specified as a character vector.

argIndex

Positive integer that indicates the position of the referencing matrix checked in the function argument list. `refmatToGeoRasterReference` includes this information in the formatted error message.

Rin

Geographic raster reference object.

Output Arguments

R

Geographic raster reference object.

Examples

Convert a referencing matrix to a geographic raster reference object:

```
% Construct a referencing matrix for a regular grid that covers the  
% entire globe with 1-degree cells.
```

```
rasterSize = [180 360];  
refmat = makerefmat( ...  
    'RasterSize', rasterSize, 'Latlim', [-90 90], ...  
    'Lonlim', [0 360])
```

```
% Convert to a geographic raster reference object.  
R = refmatToGeoRasterReference(refmat, rasterSize)
```

```
% For comparison, construct a referencing object directly.  
georasterref( ...  
    'RasterSize', rasterSize, 'Latlim', [-90 90], 'Lonlim', [0 360])
```

See Also

georasterref | refvecToGeoRasterReference

Introduced in R2011a

refmatToMapRasterReference

Referencing matrix to map raster reference object

Syntax

```
R = refmatToMapRasterReference(refmat,rasterSize)
R = refmatToMapRasterReference( ____,rasterInterpretation)
R = refmatToMapRasterReference( ____,func_name, var_name, arg_pos)
R = refmatToMapRasterReference(Rin,rasterSize, ____)
```

Description

`R = refmatToMapRasterReference(refmat,rasterSize)` constructs a map raster reference object, `R`, from a referencing matrix, `refmat`, and a size vector, `rasterSize`.

`R = refmatToMapRasterReference(____,rasterInterpretation)` uses the `rasterInterpretation` input to determine which type of map raster reference object to construct. The `rasterInterpretation` input indicates basic geometric nature of the raster, and can equal either 'cells' or 'postings'.

`R = refmatToMapRasterReference(____,func_name, var_name, arg_pos)` uses up to three optional arguments to provide additional information. This information is used to construct error messages if either the `refmat` or `rasterSize` inputs turn out to be invalid. Thus, you can use `refmatToMapRasterReference` for both validating and converting a referencing matrix. The optional inputs work just like their counterparts in the MATLAB function `validateattributes`.

`R = refmatToMapRasterReference(Rin,rasterSize, ____)` verifies that `Rin.RasterSize` is consistent with `rasterSize`, then copies `Rin` to `R`.

Input Arguments

refmat

Referencing matrix

rasterSize

Size vector [M N . . .] specifying the number of rows (*M*) and columns (*N*) in the raster or image to be associated with the `MapRasterReference` object, *R*. For convenience, `rasterSize` may be a row vector with more than two elements. This flexibility allows you to specify the size in the following way:

```
R = refmatToMapRasterReference(refmat, size(RGB))
```

where *RGB* is *M*-by-*N*-by-3. However, in such cases, only the first two elements of the size vector are actually used. The higher (non-spatial) dimensions are ignored.

rasterInterpretation

Basic geometric nature of the raster, specified as either 'cells' or 'postings'.

func_name

Name used in the formatted error message to identify the function checking the input, specified as a character vector.

var_name

Name used in the formatted error message to identify the referencing matrix, specified as a character vector.

arg_pos

Positive integer that indicates the position of the referencing matrix checked in the function argument list. `refmatToMapRasterReference` includes this information in the formatted error message.

Rin

Map raster reference object.

Output Arguments

R

Map raster reference object.

Examples

Convert a referencing matrix manually versus using the `maprasterref` function.

```
% Import a referencing matrix from a world file for a
% 2000-by-2000 orthoimage referenced to the Massachusetts
% State Plane Mainland coordinate system.
refmat = worldfileread('concord_ortho_e.tfw')

% Import the corresponding TIFF image and use its size to
% help convert the referencing matrix to a referencing object.
[X, cmap] = imread('concord_ortho_e.tif');
R = refmatToMapRasterReference(refmat, size(X))

% Use the mapbbox function to obtain the map limits independently
% of the referencing object.
bbox = mapbbox(refmat, size(X))
xLimWorld = bbox(:,1)'; % Transpose the first column
yLimWorld = bbox(:,2)'; % Transpose the second column

% Construct a referencing object directly, for comparison.
maprasterref('RasterSize', size(X), 'ColumnsStartFrom', 'north', ...
    'XLimWorld', xLimWorld, 'YLimWorld', yLimWorld)
```

See Also

`maprasterref` | `refmatToGeoRasterReference`

Introduced in R2011a

refmatToWorldFileMatrix

Convert referencing matrix to world file matrix

Syntax

```
W = refmatToWorldFileMatrix(refmat)
```

Description

`W = refmatToWorldFileMatrix(refmat)` converts the 3-by-2 referencing matrix `refmat` to a 2-by-3 world file matrix `W`.

For a definition of a referencing matrix, see `makeRefmat`.

For a definition of a world file matrix, see the `worldFileMatrix` method of the `map raster reference` and `geographic raster reference` classes.

See Also

`makeRefmat` | `worldFileMatrixToRefmat`

Introduced in R2011a

refvecToGeoRasterReference

Referencing vector to geographic raster reference object

Syntax

```
R = refvecToGeoRasterReference(refvec,rasterSize)
R = refvecToGeoRasterReference(refvec,rasterSize,funcName,varName,
argIndex)
R = refvecToGeoRasterReference(Rin,rasterSize, ___ )
```

Description

`R = refvecToGeoRasterReference(refvec,rasterSize)` constructs a geographic raster reference object, `R`, from a referencing vector, `refvec`, and a size vector, `rasterSize`.

`R = refvecToGeoRasterReference(refvec,rasterSize,funcName,varName,argIndex)` uses up to three optional arguments to provide additional information. This information is used to construct error messages if either the `refvec` or `rasterSize` inputs turn out to be invalid. Thus, you can use `refvecToGeoRasterReference` for both validating and converting a referencing vector. The optional inputs work just like their counterparts in the MATLAB function `validateattributes`.

`R = refvecToGeoRasterReference(Rin,rasterSize, ___)` verifies that `Rin.RasterSize` is consistent with `rasterSize`, then copies `Rin` to `R`.

Input Arguments

refvec

Any valid 1-by-3 referencing vector, as long as the cell size `1/refvec(1)`, northwest corner latitude `refvec(2)`, and northwest corner longitude `refvec(3)` lead to valid latitude and longitude limits when combined with the `rasterSize` vector.

rasterSize

Size vector [M N . . .] specifying the number of rows (M) and columns (N) in the raster or image to be associated with the GeoRasterReference object, R.

funcName

Name used in the formatted error message to identify the function checking the input, specified as a character vector.

varName

Name used in the formatted error message to identify the referencing vector, specified as a character vector.

argIndex

Positive integer that indicates the position of the referencing vector checked in the function argument list. `refvecToGeoRasterReference` includes this information in the formatted error message.

Rin

Geographic raster reference object.

Output Arguments

R

Geographic raster reference object.

Examples

Convert a referencing vector manually versus using the `georasterref` function.

```
% Construct a referencing vector for a regular 180-by-240 grid  
% covering an area that includes the Korean Peninsula, with 12 cells  
% per degree.  
refvec = [12 45 115];
```

```
% Convert to a geographic raster reference object:
rasterSize = [180 240];
R = refvecToGeoRasterReference(refvec, rasterSize)

% For comparison, construct a referencing object directly:
[latlim, lonlim] = limitm(zeros(rasterSize), refvec);
georasterref('RasterSize', rasterSize, 'Latlim', latlim, ...
    'Lonlim', lonlim)
```

See Also

georasterref | refmatToGeoRasterReference

Introduced in R2011a

removeExtraNaNSeparators

Clean up NaN separators in polygons and lines

Syntax

```
[xdata, ydata] = removeExtraNaNSeparators(xdata,ydata)
[xdata, ydata, zdata] = removeExtraNaNSeparators(xdata,ydata,zdata)
```

Description

`[xdata, ydata] = removeExtraNaNSeparators(xdata,ydata)` removes NaNs from the vectors `xdata` and `ydata`, leaving only isolated NaN separators. If present, one or more leading NaNs are removed entirely. If present, a single trailing NaN is preserved. NaNs are removed, but never added, so if the input lacks a trailing NaN, so will the output. `xdata` and `ydata` must match in size and have identical NaN locations.

`[xdata, ydata, zdata] = removeExtraNaNSeparators(xdata,ydata,zdata)` removes NaNs from the vectors `xdata`, `ydata`, and `zdata`, leaving only isolated NaN separators and optionally, if consistent with the input, a single trailing NaN.

Examples

```
xin = [NaN NaN 1:3 NaN 4:5 NaN NaN NaN 6:9 NaN NaN];
yin = xin;
[xout, yout] = removeExtraNaNSeparators(xin, yin);
xout
```

```
xout =
    1  2  3  NaN  4  5  NaN  6  7  8  9  NaN
```

```
xin = [NaN 1:3 NaN NaN 4:5 NaN NaN NaN 6:9]'
yin = xin;
zin = xin;
[xout, yout, zout] = removeExtraNaNSeparators(xin, yin, zin);
xout
```

```
xout =  
  1  
  2  
  3  
NaN  
  4  
  5  
NaN  
  6  
  7  
  8  
  9
```

Introduced in R2006a

resizem

Resize regular data grid

Syntax

```
Z = resizing(Z1,scale)
Z = resizing(Z1,[numrows numcols])
[Z,R] = resizing(Z1,scale,R1)
[Z,R] = resizing(Z1,[numrows numcols],R1)
[...] = resizing(..., method)
```

Description

`Z = resizing(Z1,scale)` returns a regular data grid `Z` that is `scale` times the size of the input, `Z1`. `resizing` uses interpolation to resample to a new sample density/cell size. If `scale` is between 0 and 1, the size of `Z` is smaller than the size of `Z1`. If `scale` is greater than 1, the size of `Z` is larger. For example, if `scale` is 0.5, the number of rows and the number of columns will be halved. By default, `resizing` uses nearest neighbor interpolation.

`Z = resizing(Z1,[numrows numcols])` resizes `Z1` to have `numrows` rows and `numcols` columns. `numrows` and `numcols` must be positive whole numbers.

`[Z,R] = resizing(Z1,scale,R1)` or `[Z,R] = resizing(Z1,[numrows numcols],R1)` resizes a regular data grid that is spatially referenced by `R1`. `R1` can be a referencing vector, a referencing matrix, or a geographic raster reference object.

If `R1` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z1)` and its `RasterInterpretation` must be 'cells'.

If `R1` is a referencing vector, it must be a 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If `R1` is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to/from geographic coordinates according to:

```
[lon lat] = [row col 1] * R1
```

If **R1** is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. The output **R** will be the same type as **R1** (referencing object, vector, or matrix). If **R1** is a referencing vector, the form `[numrows numcols]` is not supported and `scale` must be a scalar resizing factor.

`[...] = resize(..., method)` resizes a regular data grid using one of the following three interpolation methods:

| Method | Description |
|------------|--|
| 'nearest' | nearest neighbor interpolation (default) |
| 'bilinear' | bilinear interpolation |
| 'bicubic' | bicubic interpolation |

If the grid size is being reduced (`scale` is less than 1 or `[numrows numcols]` is less than the size of the input grid) and `method` is 'bilinear' or 'bicubic', `resize` applies a low-pass filter before interpolation, to reduce aliasing. The default filter size is 11-by-11. You can specify a different length for the default filter using:

```
[...] = resize(..., method, n)
```

`n` is an integer scalar specifying the size of the filter, which is `n`-by-`n`. If `n` is 0 or `method` is 'nearest', `resize` omits the filtering step. You can also specify your own filter `h` using:

```
[...] = resize(..., method, h)
```

`h` is any two-dimensional FIR filter (such as those returned by Image Processing Toolbox functions `ftrans2`, `fwind1`, `fwind2`, or `fsamp2`). If `H` is specified, filtering is applied even when `method` is 'nearest'.

Examples

Double the size of a grid then reduce it using different methods:

```
Z = [1 2; 3 4]
```

```
Z =
```

```
    1 2
    3 4

neargrid = resizing(Z,2)

neargrid =
    1 1 2 2
    1 1 2 2
    3 3 4 4
    3 3 4 4

bilingrid = resizing(Z,2,'bilinear')

bilingrid =
    1.0000    1.3333    1.6667    2.0000
    1.6667    2.0000    2.3333    2.6667
    2.3333    2.6667    3.0000    3.3333
    3.0000    3.3333    3.6667    4.0000

bicubgrid = resizing(bilingrid,[3 2],'bicubic')

bicubgrid =
    0.7406    1.2994
    1.6616    2.3462
    1.9718    2.5306
```

See Also

`filter2`

Introduced before R2006a

restack

Restack objects within map axes

Note `restack` will be removed in a future release. Use `uistack` instead.

Syntax

```
restack(h, position)
```

Description

`restack(h, position)` changes the stacking position of the object `h` within the axes. `h` can be a handle, a vector of handles to graphics objects, or a name recognized by `handles`. The *position* argument can have any of the following values: 'top', 'bottom', 'bot', 'up', or 'down'.

See Also

`uistack`

Introduced before R2006a

rhxrh

Intersection points for pairs of rhumb lines

Syntax

```
[newlat,newlong] = rhxrh(lat1,lon1,az1,lat2,lon2,az2)
[newlat,newlon] = rhxrh(lat1,lon1,az1,lat2,lon2,az2,units)
```

Description

`[newlat,newlong] = rhxrh(lat1,lon1,az1,lat2,lon2,az2)` returns in `newlat` and `newlon` the location of the intersection point for each pair of rhumb lines input in *rhumb line notation*. For example, the first line in the pair passes through the point `(lat1,lon1)` and has a constant azimuth of `az1`. When the two rhumb lines are identical or do not intersect (conditions that are not, in general, apparent by inspection), two NaNs are returned instead and a warning is displayed. The inputs must be column vectors.

`[newlat,newlon] = rhxrh(lat1,lon1,az1,lat2,lon2,az2,units)` specifies the units used, where `units` is any valid units. The default units are 'degrees'.

For any pair of rhumb lines, there are three possible intersection conditions: the lines are identical, they intersect once, or they do not intersect at all (except at the poles, where all nonequatorial rhumb lines meet—this is not considered an intersection). `rhxrh` does not allow multiple rhumb line intersections, although it is possible to construct cases in which such a condition occurs. See the following discussion of Limitations on page 1-1230.

Rhumb line notation consists of a point on the line and the constant azimuth of the line.

Examples

Calculate Point of Intersection of Two Paths

Given a starting point at (10°N,56°W), a plane maintains a constant heading of 35°. Another plane starts at (0°,10°W) and proceeds at a constant heading of 310° (-50°). Where would their two paths cross each other?

Calculate Point of Intersection

Use the `rhxrh` function to calculate the point of intersection of two paths.

```
[newlat,newlon] = rhxrh(10,-56,35,0,-10,310)
```

```
newlat = 26.9774
```

```
newlon = -43.4088
```

Limitations

Rhumb lines are specifically helpful in navigation because they represent lines of constant heading, whereas great circles have, in general, continuously changing heading. In fact, the Mercator projection was originally designed so that rhumb lines plot as straight lines, which facilitates both manual plotting with a straightedge and numerical calculations using a Cartesian planar representation. When a rhumb line proceeds off the left or right *edge* of this representation at some latitude, it reappears on the other edge at the same latitude and continues on the same slope. For rhumb lines where this occurs—for example, one with a heading of 85° —it is easy to imagine another rhumb line, say one with a heading of 0° , repeatedly intersecting the first. The real-world uses of rhumb lines make this merely an intellectual exercise, however, for in practice it is always clear which *crossing* line segment is relevant. The function `rhxrh` returns at most one intersection, selecting in each case that line segment containing the input starting point for its computation.

See Also

`crossfix` | `gcxgc` | `gcxsc` | `navfix` | `polyxpoly` | `scxsc`

Introduced before R2006a

rmfield

Remove dynamic property from geographic or planar vector

Syntax

```
vout = rmfield(vin,name)
vout = rmfield(vin,names)
```

Description

`vout = rmfield(vin,name)` removes the dynamic property specified by `name` from the geographic or planar vector `vin`.

`vout = rmfield(vin,names)` removes all dynamic properties specified by `names` from `vin`.

Note `rmfield` cannot remove `Metadata`, and `Geometry` properties from any geographic or planar vector. Further, it cannot remove `Latitude` and `Longitude` properties from `geopoint` and `geoshape` objects, nor `X` and `Y` properties from `mappoint` and `mapshape` objects.

Examples

Remove a Single Property from a Geopoint Vector

Create a geopoint vector with dynamic properties.

```
gp = geopoint([42 42.2],[-110.5 -110.7], 'Temperature',[65.6 63.2], 'Humidity',[44 41])
```

```
gp =
  2x1 geopoint vector with properties:
```

```
  Collection properties:
```

```
    Geometry: 'point'  
    Metadata: [1x1 struct]  
Feature properties:  
    Latitude: [42 42.2000]  
    Longitude: [-110.5000 -110.7000]  
    Temperature: [65.6000 63.2000]  
    Humidity: [44 41]
```

Remove only the Humidity property from the geopoint vector.

```
gp2 = rmfield(gp, 'Humidity')
```

```
gp2 =  
2x1 geopoint vector with properties:
```

```
Collection properties:  
    Geometry: 'point'  
    Metadata: [1x1 struct]  
Feature properties:  
    Latitude: [42 42.2000]  
    Longitude: [-110.5000 -110.7000]  
    Temperature: [65.6000 63.2000]
```

Remove Multiple Properties from a Mapshape Vector

Create a mapshape vector.

```
ms = mapshape(shaperead('tsunamis'))
```

```
ms =  
162x1 mapshape vector with properties:
```

```
Collection properties:  
    Geometry: 'point'  
    Metadata: [1x1 struct]  
Vertex properties:  
    (162 features concatenated with 161 delimiters)  
        X: [1x323 double]  
        Y: [1x323 double]  
Feature properties:
```

```

    Year: [1x162 double]
    Month: [1x162 double]
    Day: [1x162 double]
    Hour: [1x162 double]
    Minute: [1x162 double]
    Second: [1x162 double]
    Val_Code: [1x162 double]
    Validity: {1x162 cell}
    Cause_Code: [1x162 double]
    Cause: {1x162 cell}
    Eq_Mag: [1x162 double]
    Country: {1x162 cell}
    Location: {1x162 cell}
    Max_Height: [1x162 double]
    Iida_Mag: [1x162 double]
    Intensity: [1x162 double]
    Num_Deaths: [1x162 double]
    Desc_Deaths: [1x162 double]

```

Attempt to remove multiple properties from the mapshape vector.

```
s2 = rmfield(ms,{'Geometry','Second','Minute','intensity'})
```

```
s2 =
```

```
162x1 mapshape vector with properties:
```

```
Collection properties:
```

```
    Geometry: 'point'
```

```
    Metadata: [1x1 struct]
```

```
Vertex properties:
```

```
(162 features concatenated with 161 delimiters)
```

```
    X: [1x323 double]
```

```
    Y: [1x323 double]
```

```
Feature properties:
```

```
    Year: [1x162 double]
```

```
    Month: [1x162 double]
```

```
    Day: [1x162 double]
```

```
    Hour: [1x162 double]
```

```
    Val_Code: [1x162 double]
```

```
    Validity: {1x162 cell}
```

```
    Cause_Code: [1x162 double]
```

```
    Cause: {1x162 cell}
```

```
    Eq_Mag: [1x162 double]
```

```
    Country: {1x162 cell}
```

```
Location: {1x162 cell}
Max_Height: [1x162 double]
Tida_Mag: [1x162 double]
Intensity: [1x162 double]
Num_Deaths: [1x162 double]
Desc_Deaths: [1x162 double]
```

The `Second` and `Minute` properties have been removed successfully. Note that the `Geometry` property still exists because it cannot be removed. Also, `Intensity` has not been removed because property names are case-sensitive.

Input Arguments

vin — Input geographic or planar vector

geopoint, geoshape, mappoint, or mapshape object

Input geographic or planar vector, specified as a geopoint, geoshape, mappoint, or mapshape object.

name — Name of single property to remove

character vector

Name of a single property to remove, specified as a character vector. The property in name is case sensitive.

names — Name of multiple properties to remove

cell array of character vectors

Name of multiple properties to remove, specified as a cell array of character vectors. The properties in names are case-sensitive.

Output Arguments

vout — Output geographic or planar vector

geopoint, geoshape, mappoint, or mapshape object

Output geographic or planar vector, returned as a geopoint, geoshape, mappoint, or mapshape object. The object type of vout matches the object type of vin.

See Also

append | isfield | rmpop

Introduced in R2012a

rmprop

Remove property from geographic or planar vector

Syntax

```
vout = rmprop(vin,name)
vout = rmprop(vin,names)
```

Description

`vout = rmprop(vin,name)` removes the property specified by `name` from the geographic or planar vector `vin`.

`vout = rmprop(vin,names)` removes all properties specified by `names` from `vin`.

Note `rmprop` cannot remove Metadata, and Geometry properties from any geographic or planar vector. Further, it cannot remove Latitude and Longitude properties from `geopoint` and `geoshape` objects, nor X and Y properties from `mappoint` and `mapshape` objects.

Examples

Remove Single Property from a Geoshape Vector

Create a geoshape vector with dynamic properties.

```
gs = geoshape(shaperead('worldcities', 'UseGeo', true))

gs =
  318x1 geoshape vector with properties:

  Collection properties:
    Geometry: 'point'
```

```

    Metadata: [1x1 struct]
Vertex properties:
  (318 features concatenated with 317 delimiters)
    Latitude: [1x635 double]
    Longitude: [1x635 double]
Feature properties:
  Name: {1x318 cell}

```

Remove only the Name property from the geoshape vector.

```
gs2 = rmprop(gs, 'Name')
```

```

gs2 =
  318x1 geoshape vector with properties:

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Vertex properties:
  (318 features concatenated with 317 delimiters)
    Latitude: [1x635 double]
    Longitude: [1x635 double]

```

Remove Multiple Properties from a Mappoint Vector

Create a mappoint vector.

```
mp = mappoint(-33.961,18.484, 'Name', 'Cape Town', 'Temperature', 64)
```

```

mp =
  1x1 mappoint vector with properties:

Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  X: -33.9610
  Y: 18.4840
  Name: 'Cape Town'
  Temperature: 64

```

Attempt to remove multiple properties from the mappoint vector.

```
s2 = rmfield(mp,{'X', 'Name', 'temperature'})
```

```
s2 =  
1x1 mappoint vector with properties:
```

```
Collection properties:  
    Geometry: 'point'  
    Metadata: [1x1 struct]  
Feature properties:  
    X: -33.9610  
    Y: 18.4840  
    Temperature: 64
```

The Name property has been removed successfully. Note that the X property still exists because it cannot be removed. Also, the Temperature property still exists because property names are case-sensitive.

Input Arguments

vin — Input geographic or planar vector

geopoint, geoshape, mappoint, or mapshape object

Input geographic or planar vector, specified as a geopoint, geoshape, mappoint, or mapshape object.

name — Name of single property to remove

character vector

Name of a single property to remove, specified as a character vector. The character vector is case sensitive.

names — Name of multiple properties to remove

cell array of character vectors

Name of multiple properties to remove, specified as a cell array of character vectors. The character vectors are case-sensitive.

Output Arguments

vout — Output geographic or planar vector

geopoint, geoshape, mappoint, or mapshape object

Output geographic or planar vector, returned as a `geopoint`, `geoshape`, `mappoint`, or `mapshape` object. The object type of `vout` matches the object type of `vin`.

See Also

`append` | `isprop` | `rmfield`

Introduced in R2012a

rootlayr

Construct cell array of workspace variables for `mlayers` tool

Note `rootlayr` will be removed in a future release.

Syntax

```
rootlayr
```

Description

`rootlayr` allows the `mlayers` tool to be used with workspace variables. It constructs a cell array that contains all the structure variables in the current workspace. This cell array is returned in the variable `ans`, which can then be an input to `mlayers`. If there is an existing variable named `ans`, it is overwritten.

The recommended calling procedure is `rootlayr;mlayers(ans);`

Examples

`rootlayr` creates a cell array named `ans`, consisting of the three structure variables in the following workspace.

```
whos
  Name          Size          Bytes  Class
  borders       1x1            38390  struct array
  lats          2345x1         18760  double array
  lons          2345x1         18760  double array
  nation        1x1            70224  struct array
  states        1x51          254970  struct array

rootlayr
ans
ans =
```

```
[1x1 struct] 'borders'  
[1x1 struct] 'nation'  
[1x51 struct] 'states'
```

The function `mlayers(ans)` can now be used to activate the `mlayers` tool for the structures contained in `ans`.

See Also

`mlayers`

Introduced before R2006a

rotatem

Transform vector map data to new origin and orientation

Syntax

```
[lat1,lon1] = rotatem(lat,lon,origin,'forward')
[lat1,lon1] = rotatem(lat,lon,origin,'inverse')
[lat1,lon1] = rotatem(lat,lon,origin,'forward',units)
[lat1,lon1] = rotatem(lat,lon,origin,'forward',units)
```

Description

[lat1,lon1] = rotatem(lat,lon,origin,'forward') transforms latitude and longitude data (lat and lon) to their new coordinates (lat1 and lon1) in a coordinate system resulting from Euler angle rotations as specified by origin. The input origin is a three- (or two-) element vector having the form [latitude longitude orientation]. The latitude and longitude are the coordinates of the point in the original system, which is the center of the output system. The orientation is the azimuth from the new origin point to the original North Pole in the new system. If origin has only two elements, the orientation is assumed to be 0°. This origin vector might be the output of putpole or newpole.

[lat1,lon1] = rotatem(lat,lon,origin,'inverse') transforms latitude and longitude data (lat and lon) in a coordinate system *that has been transformed* by Euler angle rotations specified by origin to their coordinates (lat1 and lon1) in the coordinate system *from which they were originally transformed*. In a sense, this *undoes* the 'forward' process. Be warned, however, that if data is rotated forward and then inverted, the final data might not be identical to the original. This is because of roundoff and *data collapse* at the original and intermediate singularities (the poles).

[lat1,lon1] = rotatem(lat,lon,origin,'forward',units) and [lat1,lon1] = rotatem(lat,lon,origin,'forward',units) specify the angle units of the data, where *units* is any recognized angle unit. The default is 'radians'. Note that this default is different from that of most functions.

The rotatem function transforms vector map data to a new coordinate system.

An analytical use of the new data can be realized in conjunction with the `newpole` function. If a selected point is made the *north pole* of the new system, then when new vector data is created with `rotatem`, the distance of every data point from this new north pole is its new colatitude (90° minus latitude). The absolute difference in the great circle azimuths between every pair of points from their new *pole* is the same as the difference in their new longitudes.

Examples

What are the coordinates of Rio de Janeiro ($23^\circ\text{S}, 43^\circ\text{W}$) in a coordinate system in which New York ($41^\circ\text{N}, 74^\circ\text{W}$) is made the North Pole? Use the `newpole` function to get the origin vector associated with putting New York at the pole:

```
nylat = 41; nylon = -74;
riolat = -23; riolon = -43;
origin = newpole(nylat,nylon);
[riolat1,riolon1] = rotatem(riolat,riolon,origin,...
                           'forward','degrees')
```

```
riolat1 =
    19.8247
riolon1 =
   -149.7375
```

What does this mean? For one thing, the colatitude of Rio in this new system is its distance from New York. Compare the distance between the original points and the new colatitude:

```
dist = distance(nylat,nylon,riolat,riolon)
```

```
dist =
    70.1753
```

```
90-riolat1
```

```
ans =
    70.1753
```

See Also

`neworig` | `newpole` | `org2pol` | `putpole`

Introduced before R2006a

rotatetext

Rotate text to projected graticule

Syntax

```
rotatetext  
rotatetext(objects)  
rotatetext(objects, 'inverse')
```

Description

`rotatetext` rotates displayed text objects to account for the curvature of the graticule. The objects are selected interactively from a graphical user interface.


`rotatetext(objects)` rotates the selected objects. `objects` can be a name recognized by `handlem` or a vector of handles to displayed text objects.

`rotatetext(objects, 'inverse')` removes the rotation added by an earlier use of `rotatetext`. If omitted, `'forward'` is assumed.

Examples

Add text to a map and rotate the text to the graticule.

```
figure  
worldmap('south america')  
geoshow('landareas.shp', 'facecolor', 'yellow')  
cities = shaperead('worldcities.shp', 'UseGeoCoords', true);  
Santiago = strcmp('Santiago', {cities(:).Name});  
h=textm(cities(Santiago).Lat, cities(Santiago).Lon, ...  
        'Santiago');  
rotatetext(h)
```



Tips

You can rotate meridian and parallel labels automatically by setting the map axes `LabelRotation` property to 'on'.

See Also

`vfdtran` | `vinvtran`

Introduced before R2006a

roundn

Round to multiple of 10^n

Note roundn is not recommended. Use round instead.

Syntax

`roundn(x, n)`

Description

`roundn(x, n)` rounds each element of `x` to the nearest multiple of 10^n . `n` must be scalar, and integer-valued. For complex `x`, the imaginary and real parts are rounded independently. For `n = 0`, `roundn` gives the same result as `round`. That is, `roundn(x, 0) == round(x)`.

Examples

Round pi to the nearest hundredth.

```
roundn(pi, -2)
```

```
ans =
```

```
    3.1400
```

Round the equatorial radius of the Earth, 6378137 meters, to the nearest kilometer.

```
roundn(6378137, 3)
```

```
ans =
```

```
    6378000
```

See Also

round

Introduced before R2006a

RPCCoefficientTag

Rational Polynomial Coefficients Tag

Description

RPCCoefficientTag contains the Rational Polynomial Coefficients (RPC) TIFF tag, which describes the relationship of latitude, longitude, and height locations with row and column locations in an image.

The RPCCoefficientTag object contains properties with names and permissible values corresponding to the tag elements listed in the technical note *RPCs in GeoTIFF* technical note, viewable at http://geotiff.maptools.org/rpc_prop.html. RPCCoefficientTag is used by the functions `geotiffinfo` and `geotiffwrite`.

Creation

You can use the `map.geotiff.RPCCoefficientTag` function to create an RPCCoefficientTag object.

Properties

BiasErrorInMeters — Root mean square bias error in meters per horizontal axis

-1 (default) | nonnegative scalar

Root mean square bias error in meters per horizontal axis, specified as the number -1 or a nonnegative scalar. The value is -1 only if `BiasErrorInMeters` is not specified

Data Types: `double`

RandomErrorInMeters — Root mean square random error in meters per horizontal axis

-1 (default) | nonnegative scalar

Root mean square random error in meters, specified as the number -1 or a nonnegative scalar. The value is -1 only if `RandomErrorInMeters` is not specified.

Data Types: double

LineOffset — Line offset in pixels

0 (default) | nonnegative scalar

Line offset in pixels, specified as a nonnegative scalar, with a value of 0 by default.

Data Types: double

SampleOffset — Sample offset in pixels

0 (default) | nonnegative scalar

Sample offset in pixels, specified as a nonnegative scalar, with a value of 0 by default.

Data Types: double

GeodeticLatitudeOffset — Geodetic latitude offset in degrees

0 (default) | numeric scalar

Geodetic latitude offset in degrees, specified as a numeric scalar. The value can range from $-90 \leq \text{value} \leq 90$.

Data Types: double

GeodeticLongitudeOffset — Geodetic longitude offset in degrees

0 (default) | numeric scalar

Geodetic longitude offset in degrees, specified as a numeric scalar. The value can range from $-180 \leq \text{value} \leq 180$.

Data Types: double

GeodeticHeightOffset — Geodetic height offset in meters

0 (default) | numeric scalar

Geodetic height offset in meters, specified as a numeric scalar.

Data Types: double

LineScale — Line scale factor in pixels

1 (default) | positive scalar

Line scale factor in pixels, specified as a positive scalar.

Data Types: double

SampleScale — Sample scale factor in pixels

1 (default) | positive scalar

Sample scale factor in pixels, specified as a positive scalar.

Data Types: double

GeodeticLatitudeScale — Geodetic latitude scale in degrees

1 (default) | positive scalar

Geodetic latitude scale in degrees, specified as a positive scalar in the range (0,90].

Data Types: double

GeodeticLongitudeScale — Geodetic longitude scale in degrees

1 (default) | positive scalar

Geodetic longitude scale in degrees, specified as positive scalar in the range (0, 180].

Data Types: double

GeodeticHeightScale — Geodetic height scale factor in meters

1 (default) | positive scalar

Geodetic height scale factor in meters, specified as a positive scalar.

Data Types: double

LineNumeratorCoefficients — Coefficients for the polynomial in the numerator of the $r(n)$ equation

20-element row vector of zeros (default) | 20-element row vector

Coefficients for the polynomial in the numerator of the $r(n)$ equation, specified as a 20-element row vector of class double.

Data Types: double

LineDenominatorCoefficients — Coefficients for the polynomial in the denominator of the $r(n)$ equation

20-element row vector of zeros (default) | 20-element row vector

Coefficients for the polynomial in the denominator of the $r(n)$ equation, specified as a 20-element row vector of class double.

Data Types: double

SampleNumeratorCoefficients — Coefficients for the polynomial in the numerator of the $c(n)$ equation

20-element row vector of zeros (default) | 20-element row vector

Coefficients for the polynomial in the numerator of the $c(n)$ equation, specified as a 20-element row vector of class `double`.

Data Types: `double`

SampleDenominatorCoefficients — Coefficients for the polynomial in the denominator of the $c(n)$ equation

20-element row vector of zeros (default) | 20-element row vector

Coefficients for the polynomial in the denominator of the $c(n)$ equation, specified as a 20-element row vector of class `double`.

Data Types: `double`

Methods

`double` Convert TIFF tag property values to row vector of doubles

See Also

`geotiffinfo` | `geotiffwrite`

Introduced in R2015b

rsphere

Radii of auxiliary spheres

Syntax

```

r = rsphere('biaxial',ellipsoid)
r = rsphere('biaxial',ellipsoid,method)
r = rsphere('triaxial',ellipsoid)
r = rsphere('triaxial',ellipsoid,method)
r = rsphere('eqavol',ellipsoid)
r = rsphere('authalic',ellipsoid)
r = rsphere('rectifying',ellipsoid)
r = rsphere('curve',ellipsoid,lat)
r = rsphere('curve',ellipsoid,lat,method)
r = rsphere('euler',lat1,lon1,lat2,lon2,ellipsoid)
r = rsphere('curve', ..., angleUnits)
r = rsphere('euler', ..., angleUnits)

```

Description

`r = rsphere('biaxial',ellipsoid)` computes the arithmetic mean i.e., $(a+b)/2$ where a and b are the semimajor and semiminor axes of the specified ellipsoid. `ellipsoid` is a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`.

`r = rsphere('biaxial',ellipsoid,method)` computes the arithmetic mean if `method` is 'mean' and the geometric mean, $\sqrt{a*b}$, if `method` is 'norm'.

`r = rsphere('triaxial',ellipsoid)` computes the triaxial arithmetic mean of the semi-major axes, a , and semi-minor axes, b of the ellipsoid, $(2*a+b)/3$.

`r = rsphere('triaxial',ellipsoid,method)` computes the arithmetic mean if `method` is 'mean' and the triaxial geometric mean, $(a^2*b)^{(1/3)}$, if `method` is 'norm'.

`r = rsphere('eqavol',ellipsoid)` returns the radius of a sphere with a volume equal to that of the ellipsoid.

`r = rsphere('authalic',ellipsoid)` returns the radius of a sphere with a surface area equal to that of the ellipsoid.

`r = rsphere('rectifying',ellipsoid)` returns the radius of a sphere with meridional distances equal to those of the ellipsoid.

`r = rsphere('curve',ellipsoid,lat)` computes the arithmetic mean of the transverse and meridional radii of curvature at the latitude, `lat`. `lat` is in degrees.

`r = rsphere('curve',ellipsoid,lat,method)` computes an arithmetic mean if `method` is 'mean' and a geometric mean if `method` is 'norm'.

`r = rsphere('euler',lat1,lon1,lat2,lon2,ellipsoid)` computes the Euler radius of curvature at the midpoint of the geodesic arc defined by the endpoints (`lat1,lon1`) and (`lat2,lon2`). `lat1, lon1, lat2, and lon2` are in degrees.

`r = rsphere('curve', ..., angleUnits)` and `r = rsphere('euler', ..., angleUnits)` where `angleUnits` specifies the units of the latitude and longitude inputs as either 'degrees' or 'radians'.

Examples

Different criteria result in different spheres:

```
r = rsphere('biaxial',referenceEllipsoid('earth','km'))
```

```
r =  
  6.3674e+03
```

```
r = rsphere('triaxial',referenceEllipsoid('earth','km'))
```

```
r =  
  6.3710e+03
```

```
r = rsphere('curve',referenceEllipsoid('earth','km'))
```

```
r =  
  6.3781e+03
```


See Also

rcurve

Introduced before R2006a

satbath

Read 2-minute terrain/bathymetry from Smith and Sandwell

Syntax

```
[latgrat, longrat, z] = satbath  
[latgrat, longrat, z] = satbath(scalefactor)  
[latgrat, longrat, z] = satbath(scalefactor, latlim, lonlim)  
[latgrat, longrat, z] = satbath(scalefactor, latlim, lonlim, gsize)
```

Description

`[latgrat, longrat, z] = satbath` reads the global topography file for the entire world (`topo_8.2.img`), returning every 50th point. The result is returned as a geolocated data grid. If you use a different version of the global topography file, you need to rename it to “`topo_8.2.img`”. If the file is not found on the MATLAB path, a dialog opens to request the file.

`[latgrat, longrat, z] = satbath(scalefactor)` returns the data for the entire world, subsampled by the integer `scalefactor`. A `scalefactor` of 10 returns every 10th point. The matrix at full resolution has 6336 by 10800 points.

`[latgrat, longrat, z] = satbath(scalefactor, latlim, lonlim)` returns data for the specified region. The returned data extends slightly beyond the requested area. If omitted, the entire area covered by the data file is returned. The limits are two-element vectors in units of degrees, with `latlim` in the range `[-90 90]` and `lonlim` in the range `[-180 180]`.

`[latgrat, longrat, z] = satbath(scalefactor, latlim, lonlim, gsize)` controls the size of the graticule matrices. `gsize` is a two-element vector containing the number of rows and columns desired. If omitted, a graticule the size of the data grid is returned.

Background

This is a global bathymetric model derived from ship soundings and satellite altimetry by W.H.F. Smith and D.T. Sandwell. The model was developed by iteratively adjusting gravity

anomaly data from Geosat and ERS-1 against historical track line soundings. This technique takes advantage of the fact that gravity mirrors the large variations in the ocean floor as small variations in the height of the ocean's surface. The computational procedure uses the ship track line data to calibrate the scaling between the observed surface undulations and the inferred bathymetry. Land elevations are reduced-resolution versions of GTOPO30 data.

Examples

Read the data for the Falklands Islands (Islas Malvinas) at full resolution.

```
[latgrat,longrat,mat] = satbath(1,[-55 -50],[-65 -55]);
whos
```

| Name | Size | Bytes | Class |
|---------|---------|--------|--------------|
| latgrat | 247x301 | 594776 | double array |
| longrat | 247x301 | 594776 | double array |
| mat | 247x301 | 594776 | double array |

Tips

Land elevations are given in meters above mean sea level. The data is stored in a Mercator projection grid. As a result, spatial resolution varies with latitude. The grid spacing is 2 minutes (about 4 kilometers) at the equator.

This data is available over the Internet, but subject to copyright. The data file is binary, and should be transferred with no line-ending conversion or byte swapping. This function carries out any byte swapping that might be required. The data requires about 133 MB uncompressed.

The data and documentation are available over the Internet via <http> and anonymous <ftp>. Download the latest version of file `topo_x.2.img`, where `x` is the version number, and rename it `topo_8.w.img` for compatibility with the `satbath` function.

`satbath` returns a geolocated data grid rather than a regular data grid and a referencing vector or matrix. This is because the data is in a Mercator projection, with columns evenly spaced in longitude, but with decreasing spacing for rows at higher latitudes. Referencing vectors and matrices assume that the number of cells per degrees of latitude and longitude are both constant across a data grid.

Note For details on locating map data for download over the Internet, see the following documentation at the MathWorks Web site: “Find Geospatial Data Online”.

See Also

egm96geoid | gtopo30 | tbase

Introduced before R2006a

scaleruler

Add or modify graphic scale on map axes

Syntax

```
scaleruler  
scaleruler on  
scaleruler off  
scaleruler(property,value,...)  
h = scaleruler(...)
```

Description

`scaleruler` toggles the display of a graphic scale. If no graphic scale is currently displayed in the current map axes, one is added. If any graphic scales are currently displayed, they are removed.

`scaleruler on` adds a graphic scale to the current map axes. Multiple graphic scales can be added to the same map axes.

`scaleruler off` removes any currently displayed graphic scales.

`scaleruler(property,value,...)` adds a graphic scale and sets the properties to the values specified. You can display a list of graphic scale properties using the command `setm(h)`, where `h` is the handle to a graphic scale object. The current values for a displayed graphic scale object can be retrieved using `getm`. The properties of a displayed graphic scale object can be modified using `setm`.

`h = scaleruler(...)` returns the `hggroup` handle to the graphic scale object.


Background

Cartographers often add graphic elements to the map to indicate its scale. Perhaps the most commonly used is the graphic scale, a ruler-like object that shows distances on the ground at the correct size for the projection.

Examples

Create a map, add a graphic scale with the default settings, and shift it up a bit. Add a second scale showing nautical miles, and change the tick marks and direction.

```
figure
usamap('Texas')
geoshow('usastatelo.shp', 'FaceColor', [0.9 0.9 0])
scaleruler on
setm(handlem('scaleruler1'), ...
      'XLoc', -6.2e5, 'YLoc', 3.1e6, ...
      'MajorTick', 0:200:600)
scaleruler('units', 'nm')
setm(handlem('scaleruler2'), ...
      'YLoc', 3.0e6, ...
      'MajorTick', 0:100:300, ...
      'MinorTick', 0:25:50, ...
      'TickDir', 'down', ...
      'MajorTickLength', km2nm(25), ...
      'MinorTickLength', km2nm(12.5))
```



Object Properties

Properties That Control Appearance

Color

ColorSpec {no default}

Color of the displayed graphic scale — Controls the color of the graphic scale lines and text. You can specify a color using a vector of RGB values or one of the MATLAB predefined names. By default, the graphic scale is displayed in black ([0 0 0]).

FontAngle

{normal} | italic | oblique

Angle of the graphic scale label text — Controls the appearance of the graphic scale text components. Use any MATLAB font angles.

FontName

courier | {helvetica} | symbol | times

Font family name for all graphic scale labels — Sets the font for all displayed graphic scale labels. To display and print properly FontName must be a font that your system supports.

FontSize

scalar in units specified in FontUnits {9}

Font size — Specifies the font size to use for all displayed graphic scale labels, in units specified by the FontUnits property. The default point size is 9.

FontUnits

inches | centimeters | normalized | {points} | pixels

Units used to interpret the FontSize property — When set to normalized, the toolbox interprets the value of FontSize as a fraction of the height of the axes. For example, a normalized FontSize of 0.16 sets the text characters to a font whose height is one-tenth of the axes' height. The default units, points, are equal to 1/72 of an inch.

FontWeight

light | {normal} | demi | bold

Select bold or normal font — The character weight for all displayed graphic scale labels.

Label

character vector

Label text for the graphic scale — Contains a character vector used to label the graphic scale. The text is displayed centered on the scale. The label is often used to indicate the scale of the map, for example “1:50,000,000.”

LineWidth

scalar {0.5}

Graphic scale line width — Sets the line width of the displayed scale. The value is a scalar representing points, which is 0.5 by default.

MajorTick

vector

Graphic scale major tick locations — Sets the major tick locations for the graphic scale. The default values are chosen to give a reasonably sized scale. You can specify the locations of the tick marks by providing a vector of locations. These are usually equally spaced values as generated by `start:step:end`. The values are distances in the units of the `Units` property.

MajorTickLabel

Cell array of character vectors

Graphic scale major tick labels — Sets the text labels associated with the major tick locations. By default, the labels are identical to the major tick locations. You can override these by providing a cell array of character vectors. There must be as many character vectors as tick locations.

MajorTickLength

scalar

Length of the major tick lines — Controls the length of the major tick lines. The length is a distance in the units of the `Units` property.

MinorTick

vector

Graphic scale minor tick locations — Sets the minor tick locations for the graphic scale. The default values are chosen to give a reasonably sized scale. You can specify

the locations of the tick marks by providing a vector of locations. These are usually equally spaced values as generated by `start:step:end`. The values are distances in the units of the `Units` property.

MinorTickLabel

character vectors

Graphic scale minor tick labels — Sets the text labels associated with the minor tick locations. By default, the label is identical to the last minor tick location. You can override this by providing a character vector label.

MinorTickLength

scalar

Length of the minor tick lines — Controls the length of the minor tick lines. The length is a distance in the units of the `Units` property.

RulerStyle

{ruler} | lines | patches

Style of the graphic scale — Selects among three different kinds of graphic scale displays. The default `ruler` style looks like an axis' x-axis. The `lines` style has three horizontal lines across the tick marks. This type of graphic scale is often used on maps from the U.S. Geological Survey. The `patches` style has alternating black and white rectangles in place of lines and tick marks.

TickDir

{up} | down

Direction of the tick marks and text — Controls the direction in which the tick marks and text labels are drawn. In the default `up` direction, the tick marks and text labels are placed above the baseline, which is placed at the location given in the `XLoc` property. In the `down` position, the tick marks and labels are drawn below the baseline.

TickMode

{auto} | manual

Tick locations mode — Controls whether the tick locations and labels are computed automatically or are user-specified. Explicitly setting the tick labels or locations results in a `'manual'` tick mode. Setting any of the tick labels or locations to an empty matrix resets the tick mode to `'auto'`. Setting the tick mode to `'auto'` clears

any explicitly specified tick locations and labels, which are then replaced by default values.

XLoc

scalar

X-location of the graphic scale — Controls the horizontal location of the graphic scale within the axes. The location is specified in the axes Cartesian projected coordinates. Use `showaxes` to make the Cartesian grid labels visible. You can also move the graphic scale by dragging the baseline with the mouse.

YLoc

scalar

Y-location of the graphic scale — Controls the vertical location of the graphic scale within the axes. The location is specified in the axes Cartesian projected coordinates. Use `showaxes` to make the Cartesian grid labels visible. You can also move the graphic scale by dragging the baseline with the mouse.

Properties That Control Scaling

Azimuth

scalar

Azimuth of scale computation — The scale of a map varies, within the projection, with geographic location and azimuth. This property controls the azimuth along which the scaling between geographic and projected coordinates is computed. The azimuth is given in the current angle units of the map axes. The default azimuth is 0.

Lat

scalar

Latitude of scale computation — The scale of a map varies, within the projection, with geographic location and azimuth. This property controls the geographic location at which the scaling between geographic and projected coordinates is computed. The latitude is given in the current angle units of the map axes. The default location is the center of the displayed map.

Long

scalar

Longitude of scale computation — The scale of a map varies, within the projection, with geographic location and azimuth. This property controls the geographic location

at which the scaling between geographic and projected coordinates is computed. The longitude is given in the current angle units of the map axes. The default location is the center of the displayed map.

Radius

Name or radius of reference sphere

Reference sphere name or radius — The `radius` property controls the scaling between angular and surface distances. `radius` can be one of the character vectors supported by `km2deg`, or it can be the (numerical) radius of the desired sphere in the same units as the `Units` property. The default is 'earth'.

Units

(valid distance unit)

Surface distance units — Defines the distance units displayed in the graphic scale. `Units` can be any distance unit recognized by `unitsratio`. The distance character vector is also used in the last graphic scale text label.

Other Properties

Children

(read-only)

Name of graphic scale elements — Contains the tag assigned to the graphic elements that compose the graphic scale. All elements of the graphic scale have hidden handles except the baseline. You do not normally need to access the elements directly.

Tips

You can reposition graphic scale objects by dragging them with the mouse. You can also change their positions by modifying the `XLoc` and `YLoc` properties using `setm`.

Use `scaleruler off`, `clmo scaleruler`, or `clmo scalerulerN` to remove the scale rulers. You can also remove a graphic scale object with `delete(h)`, or `delete(handlem(`scalerulerN'))`, where `N` is the corresponding integer.

See Also

`axesscale` | `distance` | `distortcalc` | `mdistort` | `paperscale` | `surfdist`

Introduced before R2006a

scatterm

Project point markers with variable color and area

Syntax

```
scatterm(lat,lon,s,c)
scatterm(lat,lon)
scatterm(lat,lon,s)
scatterm(...,m)
scatterm(...,'filled')
scatterm(ax,...)
h = scatterm(...)
```

Description

`scatterm(lat,lon,s,c)` displays colored circles at the locations specified by the vectors `lat` and `lon` (which must be the same size). The area of each marker is determined by the values in the vector `s` (in points²) and the colors of each marker are based on the values in `c`. `s` can be a scalar, in which case all the markers are drawn the same size, or a vector the same length as `lat` and `lon`.

When `c` is a vector the same length as `lat` and `lon`, the values in `c` are linearly mapped to the colors in the current colormap. When `c` is a `length(lat)-by-3` matrix, the values in `c` specify the colors of the markers as RGB values. `c` can also be a color character vector.

`scatterm(lat,lon)` draws the markers in the default size and color.

`scatterm(lat,lon,s)` draws the markers with a single color.

`scatterm(...,m)` uses the marker `m` instead of `'o'`.

`scatterm(...,'filled')` fills the markers.


`scatterm(ax,...)` plots into axes `ax` instead of `gca`. `ax` is a handle to a map axes.

`h = scatterm(...)` returns a handle to an `hggroup`.

Examples

Plot the seamount MATLAB data as symbols with the color proportional to the height.

```
load seamount
worldmap([-49 -47.5],[-150 -147.5])
scatterm(y,x,5,z)
scaleruler
set(gca,'Visible','off')
```



See Also

`stem3m`

Introduced before R2006a

scircle1

Small circles from center, range, and azimuth

Syntax

```
[lat,lon] = scircle1(lat0,lon0,rad)
[lat,lon] = scircle1(lat0,lon0,rad,az)
[lat,lon] = scircle1(lat0,lon0,rad,az,ellipsoid)
[lat,lon] = scircle1(lat0,lon0,rad,units)
[lat,lon] = scircle1(lat0,lon0,rad,az,units)
[lat,lon] = scircle1(lat0,lon0,rad,az,ellipsoid,units)
[lat,lon] = scircle1(lat0,lon0,rad,az,ellipsoid,units,npts)
[lat,lon] = scircle1(track,...)
```

Description

`[lat,lon] = scircle1(lat0,lon0,rad)` computes small circles (on a sphere) with a center at the point `lat0,lon0` and radius `rad`. The inputs can be scalar or column vectors. The input radius is in degrees of arc length on a sphere.

`[lat,lon] = scircle1(lat0,lon0,rad,az)` uses the input `az` to define the small circle arcs computed. The arc azimuths are measured clockwise from due north. If `az` is a column vector, then the arc length is computed from due north. If `az` is a two-column matrix, then the small circle arcs are computed starting at the azimuth in the first column and ending at the azimuth in the second column. If `az = []`, then a complete small circle is computed.

`[lat,lon] = scircle1(lat0,lon0,rad,az,ellipsoid)` computes small circles on the ellipsoid defined by the input `ellipsoid`, rather than by assuming a sphere. `ellipsoid` is a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. If the semimajor axis is non-zero, `rad` is assumed to be in distance units matching the units of the semimajor axis. However, if `ellipsoid = []`, or if the semimajor axis is zero, then `rad` is interpreted as an angle and the small circles are computed on a sphere as in the preceding syntax.

```
[lat,lon] = scircle1(lat0,lon0,rad,units),  
[lat,lon] = scircle1(lat0,lon0,rad,az,units), and  
[lat,lon] = scircle1(lat0,lon0,rad,az,ellipsoid,units)
```

are all valid calling forms, which use the input units to define the angle units of the inputs and outputs. If you omit units, 'degrees' is assumed.

`[lat,lon] = scircle1(lat0,lon0,rad,az,ellipsoid,units,npts)` uses the scalar input `npts` to determine the number of points per small circle computed. The default value of `npts` is 100.

`[lat,lon] = scircle1(track,...)` uses `track` to define either a great circle or rhumb line radius. If `track = 'gc'`, then small circles are computed. If `track = 'rh'`, then the circles with radii of constant rhumb line distance are computed. If you omit `track`, 'gc' is assumed.

`mat = scircle1(...)` returns a single output argument where `mat = [lat lon]`. This is useful if a single small circle is computed.

Multiple circles can be defined from a single starting point by providing scalar `lat0,lon0` inputs and column vectors for `rad` and `az` if desired.

Examples

Create and plot a small circle centered at (0^o,0^o) with a radius of 10^o.


```
axesm('mercator','MapLatLimit',[-30 30],'MapLonLimit',[-30 30]);  
[latc,longc] = scircle1(0,0,10);  
plotm(latc,longc,'g')
```

If the desired radius is known in some nonangular distance unit, use the radius returned by the `earthRadius` function as the ellipsoid input to set the range units. (Use an empty azimuth entry to indicate a full circle.)

```
[latc,longc] = scircle1(0,0,550,[],earthRadius('nm'));  
plotm(latc,longc,'r')
```

For just an arc of the circle, enter an azimuth range.

```
[latc,longc] = scircle1(0,0,5,[-30 70]);  
plotm(latc,longc,'m')
```

Definitions

Small Circle

A *small circle* is the locus of all points an equal surface distance from a given center. For true small circles, this distance is always calculated in a great circle sense; however, the `scircle1` function allows a locus to be calculated using distances in a rhumb line sense as well. An example of a small circle is *all points exactly 100 miles from the Washington*

Monument. Parallels on the globe are all small circles. Great circles are a subset of small circles, specifically those with a radius of 90° or its angular equivalent, so all meridians on the globe are small circles as well.

Small Circle Notation

Small circle notation consists of a center point and a radius in units of angular arc length.

See Also

scircle2 | scircleg | track | track1 | track2 | trackg

Introduced before R2006a

scircle2

Small circles from center and perimeter

Syntax

```
[lat,lon] = scircle2(lat1,lon1,lat2,lon2)
[lat,lon] = scircle2(lat1,lon1,lat2,lon2,ellipsoid)
[lat,lon] = scircle2(lat1,lon1,lat2,lon2,units)
[lat,lon] = scircle2(lat1,lon1,lat2,lon2,ellipsoid,units)
[lat,lon] = scircle2(lat1,lon1,lat2,lon2,ellipsoid,units,npts)
[lat,lon] = scircle2(track,...)
mat = scircle2(...)
mat = [lat lon]
```

Description

`[lat,lon] = scircle2(lat1,lon1,lat2,lon2)` computes small circles (on a sphere) with centers at the points `lat1,lon1` and points on the circles at `lat2,lon2`. The inputs can be scalar or column vectors.

`[lat,lon] = scircle2(lat1,lon1,lat2,lon2,ellipsoid)` computes the small circle on the ellipsoid defined by the input `ellipsoid`, rather than by assuming a sphere. `ellipsoid` is a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. Default is a unit sphere.

`[lat,lon] = scircle2(lat1,lon1,lat2,lon2,units)` and `[lat,lon] = scircle2(lat1,lon1,lat2,lon2,ellipsoid,units)` are valid calling forms, which use the input `units` to define the angle units of the inputs and outputs. If you omit `units`, 'degrees' is assumed.

`[lat,lon] = scircle2(lat1,lon1,lat2,lon2,ellipsoid,units,npts)` uses the scalar input `npts` to determine the number of points per track computed. The default value of `npts` is 100.

`[lat,lon] = scircle2(track,...)` uses `track` to define either a great circle or a rhumb line radius. If `track` = 'gc', then small circles are computed. If `track` =

'rh', then circles with radii of constant rhumb line distance are computed. If you omit track, 'gc' is assumed.

`mat = scircle2(...)` returns a single output argument where `mat = [lat lon]`. This is useful if a single circle is computed.


Multiple circles can be defined from a single center point by providing scalar `lat1, lon1` inputs and column vectors for the points on the circumference, `lat2, lon2`.

Examples

Plot Locus of Points Equidistant from New Delhi

Plot the locus of all points the same distance from New Delhi as Kathmandu.

```
axesm('mercator', 'MapLatLimit', [0 40], 'MapLonLimit', [60 110]);
load coastlines
% For reference
plotm(coastlat, coastlon, 'k');
% New Delhi
lat1 = 29; lon1 = 77.5;
% Kathmandu
lat2 = 27.6; lon2 = 85.5;
% Plot the cities
plotm([lat1 lat2], [lon1 lon2], 'b*')
[latc, lonc] = scircle2(lat1, lon1, lat2, lon2);
plotm(latc, lonc, 'b')
```



Definitions

Small Circle

A *small circle* is the locus of all points an equal surface distance from a given center. For true small circles, this distance is always calculated in a great circle sense. However, the `scircle2` function allows a locus to be calculated using distances in a rhumb line sense as well. An example of a small circle is *all points exactly 100 miles from the Washington Monument*.

See Also

scircle1 | track | track1 | track2

Introduced before R2006a

scircleg

Small circle defined via mouse input

Syntax

```
h = scircleg(ncirc)
h = scircleg(ncirc,npts)
h = scircleg(ncirc,linestyle)
h = scircleg(ncirc,PropertyName,PropertyValue,...)
[lat,lon] = scircleg(ncirc,npts,...)
h = scircleg(track,ncirc,...)
```

Description

`h = scircleg(ncirc)` brings forward the current map axes and waits for the user to make $(2 * \text{ncirc})$ mouse clicks. The output `h` is a vector of handles for the `ncirc` small circles, which are then displayed.

`h = scircleg(ncirc,npts)` specifies the number of plotting points to be used for each small circle. `npts` is 100 by default.

`h = scircleg(ncirc,linestyle)` where `linestyle` is a linespec that specifies the style of the line used for the displayed small circles.

`h = scircleg(ncirc,PropertyName,PropertyValue,...)` allows property name/property value pairs to be set, where `PropertyName` and `PropertyValue` are recognized by the line function.

`[lat,lon] = scircleg(ncirc,npts,...)` returns the coordinates of the plotted points rather than the handles of the small circles. Successive circles are stored in separate columns of `lat` and `lon`.

`h = scircleg(track,ncirc,...)` specifies the logic with which ranges are calculated. If `track` is 'gc' (the default), great circle distance is used. If `track` is 'rh', rhumb line distance is used.

This function is used to define small circles for display using mouse clicks. For each circle, two clicks are required: one to mark the center of the circle and one to mark any point on the circle itself, thereby defining the radius.

Background

A small circle is the locus of all points an equal surface distance from a given center. For true small circles, this distance is always calculated in a great circle sense; however, the `scircleg` function allows a locus to be calculated using distances in a rhumb line sense as well. You can modify the circle after creation by **shift**+clicking it. The circle is then in edit mode, during which you can change the size and position by dragging control points, or by entering values into a control panel. **Shift**+clicking again exits edit mode.

See Also

`scircle1` | `scircle2`

Introduced before R2006a

SCXSC

Intersection points for pairs of small circles

Syntax

```
[lat,lon] = scxsc(lat1,lon1,range1,lat2,lon2,range2)
[lat,lon] = scxsc(lat1,lon1,range1,lat2,lon2,range2,units)
latlon = scxsc( ___ )
```

Description

`[lat,lon] = scxsc(lat1,lon1,range1,lat2,lon2,range2)` returns in `lat` and `lon` the locations where pairs of small circles intersect. The small circles are defined using *small circle notation*, which consists of a center point and a radius in units of angular arc length. For example, the first small circle in a pair would be centered on the point `(lat1,lon1)` with a radius of `range1` (in angular units).

For any pair of small circles, there are four possible intersection conditions: the circles are identical, they do not intersect, they are tangent to each other and hence they intersect once, or they intersect twice.

`[lat,lon] = scxsc(lat1,lon1,range1,lat2,lon2,range2,units)` specifies the angular units used for all inputs, where `units` is any valid angular unit.

`latlon = scxsc(___)` returns a single output consisting of the concatenated latitude and longitude coordinates of the small circle intersection points.

Examples

Find Intersection Points of Two Small Circles

Given a small circle centered at (10°S,170°W) with a radius of 20° (~1200 nautical miles), where does it intersect with a small circle centered at (3°N, 179°E), with a radius of 15° (~900 nautical miles)?

```
[newlat,newlon] = scxsc(-10,-170,20,3,179,15)
```

```
newlat =  
-8.8368    9.8526
```

```
newlon =  
169.7578 -167.5637
```

Note that in this example, the two small circles cross the date line.

Input Arguments

lat1, lon1 — Center coordinate of first small circle

numeric scalar | n -element numeric vector

Latitude or longitude coordinate of the center of the first small circle in each pair, specified as one of these values.

- A numeric scalar to find the intersection of a single pair of small circles.
- A n -element numeric vector to find the intersection of n pairs of small circles.

`lat1` and `lon1` must have the same length.

Example: -10

Example: [-10 20 90 -45]

range1 — Radius of first small circle

positive numeric scalar | n -element vector of positive numbers

Radius of the first small circle of each pair, in angular units, specified as one of these values.

- A positive numeric scalar to find the intersection of a single pair of small circles.
- A n -element vector of positive numbers to find the intersection of n pairs of small circles. The length of `range1` matches the length of `lat1` and `lon1`.

Example: 20

Example: [20 10 45 45]

lat2, lon2 — Center coordinate of second small circle

numeric scalar | numeric vector

Latitude or longitude coordinate of the center of the second small circle in each pair, specified as one of these values.

- A numeric scalar to find the intersection of a single pair of small circles.
- A n -element numeric vector to find the intersection of n pairs of small circles.

`lat2` and `lon2` must have the same length as `lat1` and `lon1`.

Example: 3

Example: [3 30 85 -45]

range2 — Radius of second small circle

positive numeric scalar | n -element vector of positive numbers

Radius of the second small circle of each pair, in angular units, specified as one of these values.

- A positive numeric scalar to find the intersection of a single pair of small circles.
- A n -element vector of positive numbers to find the intersection of n pairs of small circles. The length of `range2` matches the length of `lat2` and `lon2`.

Example: 15

Example: [15 15 45 50]

units — Angular units

'degrees' (default) | 'radians'

Angular units, specified as 'degrees' or 'radians'.

Output Arguments

lat, lon — Coordinates of small circle intersections

2-element vector | n -by-2 matrix

Coordinates of small circle intersections, returned as one of the following.

- 2-element vector when you find the intersection of a single pair of small circles.
- n -by-2 matrix when when you find the intersection of n pairs of small circles.

If a pair of small circles do not intersect, or are identical, then `scxsc` displays a warning and returns NaNs for the latitude and longitude coordinates of the intersection points. If a pair of small circles are tangent, then the single intersection point is returned twice.

latlon — Concatenated coordinates of small circle intersections

4-element vector | n -by-4 matrix

Concatenated coordinates of small circle intersections, returned as one of the following. This output is identical to `[lat lon]`.

- 4-element vector when you find the intersection of a single pair of small circles.
- n -by-4 matrix when you find the intersection of n pairs of small circles.

If a pair of small circles do not intersect, or are identical, then `scxsc` displays a warning and returns NaNs for the latitude and longitude coordinates of the intersection points. If a pair of small circles are tangent, then the single intersection point is returned twice.

Tips

Great circles are a subset of small circles — a great circle is just a small circle with a radius of 90° . This provides two methods of notation for defining great circles. *Great circle notation* consists of a point on the circle and an azimuth at that point. *Small circle notation* for a great circle consists of a center point and a radius of 90° (or its equivalent in radians).

See Also

`crossfix` | `gc2sc` | `gcxgc` | `gcxsc` | `polyxpoly` | `rxhrh`

Introduced before R2006a

sdtsdemread

Read data from SDTS raster/DEM data set

Syntax

```
[Z, R] = sdtsdemread(filename)
```

Description

`[Z, R] = sdtsdemread(filename)` reads data from an SDTS DEM data set. `Z` is a matrix containing the elevation values. `R` is a referencing matrix (see `makerefmat`). NaNs are assigned to elements of `Z` corresponding to null data values or fill data values in the cell module.

`filename` can be the name of the SDTS catalog directory file (`*CATD.DDF`) or the name of any of the other files in the data set. `filename` can include the directory name; otherwise `filename` is searched for in the current directory and the MATLAB path. If any of the files specified in the catalog directory are missing, `sdtsdemread` fails.

Examples

```
[Z, R] = sdtsdemread('9129CATD.ddf');  
mapshow(Z,R, 'DisplayType', 'contour')
```

Tips

Elevation values can be imported with `sdtsdemread` from DEMs that use the SPRE Raster Profile (in use since January, 2001) as well as from older SDTS DEM data sets. Under this profile, elevations can be encoded either as 32-bit floating-point numbers (when their units are “decimal meters”), or as 16-bit integers (when units are “feet” or “meters”). The output class from `sdtsdemread` for both types of elevation encoding is `double`.

Note For details on locating map data for download over the Internet, see the following documentation at the MathWorks Web site: “Find Geospatial Data Online”.

See Also

`arcgridread` | `makerefmat` | `mapshow` | `sdtsinfo`

Introduced before R2006a

sdtsinfo

Information about SDTS data set

Syntax

```
info = sdtsinfo(filename)
```

Description

`info = sdtsinfo(filename)` returns a structure whose fields contain information about the contents of a SDTS data set.

`filename` is a string scalar or character vector that specifies the name of the SDTS catalog directory file, such as `7783CATD.DDF`. The filename can also include the directory name. If `filename` does not include the directory, then it must be in the current directory or in a directory on the MATLAB path. If `sdtsinfo` cannot find the SDTS catalog file, it returns an error.

If any of the other files in the data set as specified by the catalog file is missing, a warning message is returned. Subsequent calls to read data from the file might also fail.

Field Descriptions

The `info` structure contains the following fields:

| | |
|----------------|--|
| Filename | Name of the catalog directory file of the SDTS transfer set, specified as a character vector. |
| Title | Name of the data set, specified as a character vector. |
| ProfileID | Profile Identifier, e.g., 'SRPE: SDTS RASTER PROFILE and EXTENSIONS', specified as a character vector. |
| ProfileVersion | Profile Version Identifier, e.g., 'VER 1.1 1998 01', specified as a character vector. |

| | |
|------------------|---|
| MapDate | Date associated with the cartographic information contained in the data set, specified as a character vector. |
| DataCreationDate | Creation date of the data set, specified as a character vector. |
| HorizontalDatum | Horizontal datum to which the data is referenced, specified as a character vector. |
| MapRefSystem | Projection and reference system used, specified as one of the following values: 'GEO', 'SPCS', 'UTM', 'UPS', or ''. |
| ZoneNumber | Scalar value representing the zone number |
| XResolution | Scalar value representing the X component of the horizontal coordinate resolution |
| YResolution | Scalar value representing the Y component of the horizontal coordinate resolution |
| NumberOfRows | Scalar value representing the number of rows of the DEM |
| NumberOfCols | Scalar value representing the number of columns of the DEM |
| HorizontalUnits | Units used for the horizontal coordinate values, specified as a character vector. |
| VerticalUnits | Units used for the vertical coordinate values, specified as a character vector. |
| MinElevation | Scalar value of the minimum elevation value for the data set |
| MaxElevation | Scalar value of the maximum elevation value for the data set |

Examples

```
info = sdtsinfo('9129CATD.DDF');
```

See Also

[makerefmat](#) | [sdtsdemread](#)

Introduced before R2006a

sectorg

Sector of small circle defined via mouse input

Syntax

sectorg

Description

sectorg prompts the user to indicate by two successive mouse clicks two points that define the center and radius of a small circle arc. By default, the angular width of the sector is 60°. The sector is constructed using the vector defined by the mouse clicks as the reference azimuth (defined to run through the center of the sector).

Once a sector has been drawn, **Shift**+clicking on it displays four control points (center point, arc resize, radial resize, and rotation controls), and the associated **Sector** control window. You can graphically interact with sectors as follows:

- To translate the circle, click and drag the center (o) control.
- To change the arc size, click and drag the resize control (square).
- To change the radial size of the sector, click and drag the radial control (down triangle).
- To rotate the arc, click and drag the rotation control (x).

You can also modify a selected sector by entering the appropriate values in the **Sector** control window and then pressing **Enter** or clicking the **Close** button. Display of the control panel is toggled by **Shift**+clicking the sector. If you select multiple sectors, a separate **Sector** control window will appear for each one.

Tips

Sector control windows are superimposed at the same location. A valid map axes must exist prior to running this function.

See Also

scircleg | trackg

Introduced before R2006a

setltn

Convert data grid rows and columns to latitude-longitude

Syntax

```
[lat, lon] = setltn(Z, R, row, col)
[lat, lon, indxPointOutsideGrid] = setltn(Z, R, row, col)
latlon = setltn(Z, R, row, col)
```

Description

`[lat, lon] = setltn(Z, R, row, col)` returns the latitude and longitudes associated with the input row and column coordinates of the regular data grid `Z`. `R` can be a geographic raster reference object, a referencing vector, or a referencing matrix.

If `R` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z)`.

If `R` is a referencing vector, it must be 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If `R` is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to/from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If `R` is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. Points falling outside the grid are ignored in `row` and `col`. All input angles are in degrees.

`[lat, lon, indxPointOutsideGrid] = setltn(Z, R, row, col)` returns the indices of the elements of the `row` and `col` vectors that lie outside the input grid. The outputs `lat` and `lon` always ignore these points; the third output accounts for them.

`latlon = settln(Z, R, row, col)` returns the coordinates in a single two-column matrix of the form [latitude longitude].

Examples

Find the coordinates of row 45, column 65 of `topo`:

```
load topo
[lat,lon,indxPointOutsideGrid] = settln(topo,topolegend,45,65)

lat =
    -45.5000
lon =
     64.5000
indxPointOutsideGrid = [] % Empty because the point is valid
```

See Also

`ltln2val` | `pix2latlon` | `setpostn`

Introduced before R2006a

setm

Set properties of map axes and graphics objects

Syntax

```
setm(h,MapAxesPropertyName,PropertyValue,...)
setm(texthdl,'MapPosition',position)
setm(surfhdl,'Graticule',lat,lon,alt)
setm(surfhdl,'MeshGrat',npts,alt)
```

Description

`setm(h,MapAxesPropertyName,PropertyValue,...)`, where `h` is a valid map axes handle, sets the map axes properties specified in the input list. The map axes properties must be recognized by `axesm`.

`setm(texthdl,'MapPosition',position)` alters the position of the projected text object specified by its handle to the [latitude longitude] or the [latitude longitude altitude] specified by the position vector.

`setm(surfhdl,'Graticule',lat,lon,alt)` alters the graticule of the projected surface object specified by its handle. The graticule is specified by the latitude and longitude matrices, specifying locations of the graticule vertices. The altitude can be specified by a scalar, or by a matrix providing a value for each vertex.


`setm(surfhdl,'MeshGrat',npts,alt)` alters the mesh graticule of projected surface objects displayed using the `meshm` function. In this case, the two-element vector `npts` specifies the graticule size in the manner described under `meshm`. The altitude can be a scalar or a matrix with a size corresponding to `npts`.

Examples

Display a map axes and alter it:


```
axesm('bonne','Frame','on','Grid','on')
```

The standard Bonne projection has a standard parallel at 30°N.



Setting this standard parallel to 0° results in a Sinusoidal projection:

```
setm(gca, 'MapParallels', 0)
```



See Also

`axesm` | `getm`

Introduced before R2006a

setpostn

Convert latitude-longitude to data grid rows and columns

Syntax

```
[row, col] = setpostn(Z, R, lat, lon)
indx = setpostn(...)
[row, col, indxPointOutsideGrid] = setpostn(...)
```

Description

`[row, col] = setpostn(Z, R, lat, lon)` returns the row and column indices of the regular data grid `Z` for the points specified by the vectors `lat` and `lon`. `R` can be a geographic raster reference object, a referencing vector, or a referencing matrix.

If `R` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z)`.

If `R` is a referencing vector, it must be 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If `R` is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to/from geographic coordinates according to:

$$[\text{lon } \text{lat}] = [\text{row } \text{col } 1] * R$$

If `R` is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. Points falling outside the grid are ignored in `row` and `col`. All input angles are in degrees.

`indx = setpostn(...)` returns the indices of `Z` corresponding to the points in `lat` and `lon`. Points falling outside the grid are ignored in `indx`.

`[row, col, indxPointOutsideGrid] = setpostn(...)` returns the indices of `lat` and `lon` corresponding to points outside the grid. These points are ignored in `row` and `col`.

Examples

What are the matrix coordinates in `topo` of Denver, Colorado, at (39.7°N,105°W)?

```
load topo
[row,col] = setpostn(topo,topolegend,39.7,105)

row =
    130
col =
    105
```

See Also

`latlon2pix` | `l2ln2val` | `setl2ln`

Introduced before R2006a

servers

Return URLs of unique WMS servers

Syntax

```
serverURLs = servers(layers)
```

Description

`serverURLs = servers(layers)` returns the URLs of unique servers associated with Web map service layers, `layers`.

Examples

Find all unique URLs of government servers

Find the URLs for government servers.

```
layers = wmsfind('*.gov*', 'SearchField', 'serverurl');
serverURLs = servers(layers);
sprintf('%s\n', serverURLs{:})
```

ans =

```
http://atlas.resources.ca.gov/ArcGIS/Services/Atmosphere_Climate/CaliforniaWeatherFore
http://atlas.resources.ca.gov/ArcGIS/Services/Atmosphere_Climate/RIDGE-345min/MapServer
http://atlas.resources.ca.gov/ArcGIS/Services/Atmosphere_Climate/RIDGE_Precip_Radar/Map
http://atlas.resources.ca.gov/ArcGIS/Services/Atmosphere_Climate/RIDGE_Radar_TimeSeries
http://atlas.resources.ca.gov/ArcGIS/Services/Atmosphere_Climate/USCityWeatherForecast
http://atlas.resources.ca.gov/ArcGIS/Services/Base_Maps/JacksonStForest/MapServer/WMSSe
http://atlas.resources.ca.gov/ArcGIS/Services/Base_Maps/Topo_GrayScale/MapServer/WMSSe
http://atlas.resources.ca.gov/ArcGIS/Services/Base_Maps/Topo_Hillshade/MapServer/WMSSe
http://atlas.resources.ca.gov/ArcGIS/Services/Base_Maps/Topo_Regular/MapServer/WMSServe
```

.

List server URLs that contain a temperature layer along with the number of temperature layers

Find server URLs that contain temperature layers and return them in a Web Map Service Layers (WMSLayer) object.

```
temperature = wmsfind('temperature');
serverURLs = servers(temperature);
for k=1:numel(serverURLs)
    querystr = serverURLs{k};
    layers = refine(temperature,querystr, ...
        'SearchFields', 'serverurl');
    fprintf('Server URL\n%s\n', layers(1).ServerURL);
    fprintf('Number of layers: %d\n\n', numel(layers));
end
```

Server URL

```
http://www.ifremer.fr/thredds/wms/METEOFRANCE-EUR-SST_L3MONOSENSOR_NRT-OBS_SEVIRI_1_1H
Number of layers: 2
```

Server URL

```
http://www.ifremer.fr/thredds/wms/METEOFRANCE-EUR-SST_L3MONOSENSOR_NRT-OBS_SEVIRI_1_1H
Number of layers: 2
```

Server URL

```
http://www.ifremer.fr/thredds/wms/METEOFRANCE-EUR-SST_L3MONOSENSOR_NRT-OBS_TMI-EUR-MYOC
Number of layers: 2
```

.

Input Arguments

Layers — Layers to provide server URLs

array of WMSLayer objects

Layers to provide server URLs, specified as an array of WMSLayer objects.

Output Arguments

serverURLs — URLs of unique servers

cell array of character vectors

URLs of unique servers, returned as a cell array of character vectors.

See Also

`refine` | `serverTitles` | `wmsfind`

Introduced in R2009b

serverTitles

Return titles of unique WMS servers

Syntax

```
titles = serverTitles(layers)
```

Description

`titles = serverTitles(layers)` returns the titles of unique servers associated with Web map service layers, `layers`.

Examples

List Titles of Unique Government Servers

List titles of unique government servers

```
layers = wmsfind('*.gov*', 'SearchField', 'serverurl');
titles = serverTitles(layers);
sprintf('%s\n', titles{:})
```

```
Atmosphere_Climate/CaliforniaWeatherForecasts
Atmosphere_Climate_RIDGE-345min
WMS
Atmosphere_Climate_RIDGE_Radar_TimeSeries
Atmosphere_Climate/USCityWeatherForecast
Base_Maps_JacksonStForest
Base_Maps_Topo_GrayScale
Base_Maps_Topo_Hillshade
Base_Maps_Topo_Regular
Base_Maps_Topo_Transparent
WMS
Base_Maps/california_hillshade_base_map
Boundaries/CountyBoundaries
```

```
Boundaries/ElectedOfficials
Boundaries_SRA_wgs84wm
Environment_Watersheds
Environment/bond_projects
GeoScience/CSMW_Geology
GeoScience/California_Fire_History
GeoScience/GeoMAC_ActiveFires
GeoScience_GeoMAC_InActiveFires
GeoScience_HazardMaps_09_01_2009_Fire
GeoScience/US_Fire_History
Health_ADP_Treatment_Providers
.
.
.
```

Input Arguments

layers — Layers to provide server URLs

array of WMSLayer objects

Layers to provide server URLs, specified as an array of WMSLayer objects.

Output Arguments

titles — Titles of unique WMS servers

cell array of character vectors

Titles of unique WMS servers, returned as a cell array of character vectors.

See Also

`servers` | `wmsfind`

Introduced in R2009b

shaderel

Construct cdata and colormap for shaded relief

Syntax

```
[cindx,cimap,clim] = shaderel(X,Y,Z,cmap)
[cindx,cimap,clim] = shaderel(X,Y,Z,cmap,[azim elev])
[cindx,cimap,clim] = shaderel(X,Y,Z,cmap,[azim elev],cmapl)
[cindx,cimap,clim] = shaderel(X,Y,Z,cmap,[azim elev],cmapl,clim)
```

Description

`[cindx,cimap,clim] = shaderel(X,Y,Z,cmap)` constructs the colormap and color indices to allow a surface to be displayed in colored shaded relief. The colors are proportional to the magnitude of `Z`, but modified by shades of gray based on the surface normals to simulate surface lighting. This representation allows both large and small-scale differences to be seen. `X`, `Y`, and `Z` define the surface. `cmap` is the colormap used to create the new shaded colormap `cimap`. `cindx` is a matrix of color indices to `cimap`, based on the elevation and surface normal of the `Z` matrix element. `clim` contains the color axis limits.

`[cindx,cimap,clim] = shaderel(X,Y,Z,cmap,[azim elev])` places the light at the specified azimuth and elevation. By default, the direction of the light is East (90° azimuth) at an elevation of 45°.


`[cindx,cimap,clim] = shaderel(X,Y,Z,cmap,[azim elev],cmapl)` chooses the number of grays to give a `cimap` of length `cmapl`. By default, the number of grayscales is chosen to keep the shaded colormap below 256. If the vector of azimuth and elevation is empty, the default locations are used.

`[cindx,cimap,clim] = shaderel(X,Y,Z,cmap,[azim elev],cmapl,clim)` uses the color limits to index `Z` into `cmap`.

Examples

Display the peaks surface with a shaded colormap:

```
[X,Y,Z] = peaks(100);  
cmap = hot(16);  
[cindx,cimap,clim] = shaderel(X,Y,Z,cmap);  
surf(X,Y,Z,cindx); colormap(cimap); caxis(clim)  
shading flat
```



Tips

This function effectively multiplies two colormaps, one with color based on elevation, the other with a grayscale based on the slope of the surface, to create a new colormap. This produces an effect similar to using a light on a surface, but with all of the visible colors actually in the colormap. Lighting calculations are performed on the unprojected data.

See Also

`caxis` | `colormap` | `light` | `meshlsm` | `surf` | `surflsm`

Introduced before R2006a

shapeinfo

Information about shapefile

Syntax

```
info = shapeinfo(filename)
```

Description

`info = shapeinfo(filename)` returns a structure, `info`, whose fields contain information about the contents of a shapefile. `filename` can be the base name or the full name of any one of the component files. `shapeinfo` reads all three files as long as they exist in the same folder and the unit of length or angle is not specified. If the main file (with extension `.SHP`) is missing, `shapeinfo` returns an error. If either of the other files is missing, `shapeinfo` returns a warning.

Input Arguments

filename — File name

string scalar | character vector

File name of the shapefile, specified as a string scalar or character vector. `filename` can be the base name or the full name of any one of the component files.

Output Arguments

info — Information about shapefile contents

structure

Information about shapefile contents, returned as a structure contains the following fields.

| | |
|-------------|--|
| Filename | Char array containing the names of the files that were read |
| ShapeType | Character vector containing the shape type |
| BoundingBox | Numerical array of size 2-by- <i>N</i> that specifies the minimum (row 1) and maximum (row 2) values for each dimension of the spatial data in the shapefile |
| Attributes | Structure array of size 1-by-numAttributes that describes the attributes of the data. The structure contains these fields: <ul style="list-style-type: none">• Name — Character vector containing the attribute name as given in the xBASE table• Type — Character vector specifying the MATLAB class of the attribute data returned by <code>shaperead</code>. The following attribute (xBASE) types are supported: Numeric, Floating, Character, and Date |
| NumFeatures | The number of spatial features in the shapefile |

Tips

`shapeinfo` cannot tell you which coordinate system the data in a shapefile uses. Coordinates can be either planar (x, y) or geographic (lat, lon) and have a variety of units. This information can be critical to the proper display of shapefile vector data. For more information on this topic, see “Mapstructs and Geostructs”.

See Also

`shaperead` | `shapewrite`

Topics

“Geographic Data Structures”

Introduced before R2006a

shaperead

Read vector features and attributes from shapefile

Syntax

```
S = shaperead(filename)
S = shaperead(filename,Name,Value)
[S,A] = shaperead( ___ )
```

Description

`S = shaperead(filename)` reads the shapefile, `filename`, and returns an N -by-1 geographic data structure array in projected map coordinates (a mapstruct). The geographic data structure combines geometric and feature attribute information. `shaperead` supports the ordinary 2-D shape types: 'Point', 'Multipoint', 'PolyLine', and 'Polygon'.

`S = shaperead(filename,Name,Value)` returns a subset of the shapefile contents in `S`, as determined by the name-value pair arguments. Use `RecordNumbers`, `BoundingBox`, and `Selector` to select which features to read. If you use more than one of these parameters in the same call, you receive the intersection of the records that match the individual specifications. For instance, if you specify values for both `RecordNumbers` and `BoundingBox`, you import only those features with record numbers that appear in your list and that also have bounding boxes intersecting the specified bounding box.

If you do not specify any parameters, `shaperead` returns an entry for every non-null feature and creates a field for every attribute.

`[S,A] = shaperead(___)` returns an N -by-1 geographic data structure array, `S`, containing geometric information, and a parallel N -by-1 attribute structure array, `A`, containing feature attribute information.

Examples

Read entire contents of shapefile

Read the entire `concord_roads.shp` shapefile, including the attributes in `concord_roads.dbf`. The `shaperead` function returns a mapstruct with X and Y coordinate vectors.

```
S = shaperead('concord_roads.shp')
```

```
S = 609x1 struct array with fields:  
  Geometry  
  BoundingBox  
  X  
  Y  
  STREETNAME  
  RT_NUMBER  
  CLASS  
  ADMIN_TYPE  
  LENGTH
```

Read portion of shapefile based on bounding box

Specify a bounding box to limit the data returned by `shaperead`. In addition, specify the names of the attributes you want to read.

```
bbox = [2.08 9.11; 2.09 9.12] * 1e5;  
S = shaperead('concord_roads', 'BoundingBox', bbox, ...  
             'Attributes', {'STREETNAME', 'CLASS'})
```

```
S = 87x1 struct array with fields:  
  Geometry  
  BoundingBox  
  X  
  Y  
  STREETNAME  
  CLASS
```

Read road data by class from shapefile

Read road data only for class 4 and higher road segments that are at least 200 meters in length. Note the use of an anonymous function in the selector.

```
S = shaperead('concord_roads.shp', 'Selector', ...
             {@(v1,v2) (v1 >= 4) && (v2 >= 200)}, 'CLASS', 'LENGTH');
```

```
S = 115x1 struct array with fields:
    Geometry
    BoundingBox
    X
    Y
    STREETNAME
    RT_NUMBER
    CLASS
    ADMIN_TYPE
    LENGTH
```

Determine the number of roads of each class.


```
n = histcounts([S.CLASS], 'BinLimits', [1 7], 'BinMethod', 'integer')
```

```
n = 1x7
```

```
    0    0    0    7   93   15    0
```

Display a histogram of the number of roads that fall in each category of length.

```
figure
histogram([S.LENGTH])
```



Read shapefile and return geostruct

Read a shapefile of worldwide city names and locations given in latitude and longitude. Note how `shaperead` returns a `geostruct` because you specified the `'UseGeoCoords'` parameter.

```
S = shaperead('worldcities.shp', 'UseGeoCoords', true)
```

```
S = 318x1 struct array with fields:  
  Geometry  
  Lon
```

Lat
Name

Input Arguments

filename — File name

character vector | string scalar

File name, specified as a string scalar or character vector. `filename` refers to the base name or full name of one of the component files in a shapefile. If the main file (with extension `.shp`) is missing, `shaperead` throws an error. If either of the other files is missing, `shaperead` issues a warning.

Make sure that your machine is set to the same character encoding scheme as the data you are importing. For example, if you are trying to import a shapefile that contains Japanese characters, configure your machine to support the Shift-JIS encoding scheme.

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (`' '`). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

Example: `'Attributes', {'STREETNAME', 'LENGTH'}`

RecordNumbers — Record numbers

vector of integers

Record numbers, specified as the comma-separated pair consisting of `'RecordNumbers'` and a vector of integers. Use the parameter `RecordNumbers` to import only features with listed record numbers.

Data Types: double

BoundingBox — Bounding box

2-by-2 matrix

Bounding box, specified as the comma-separated pair consisting of 'BoundingBox' and a 2-by-2 matrix. BoundingBox has the form [xmin, ymin; xmax, ymax], for map coordinates, or [lonmin, latmin; lonmax, latmax] for geographic coordinates. Use the parameter BoundingBox to import only features whose bounding boxes intersect the specified box. The shaperead function does not trim features that partially intersect the box.

Data Types: double

Selector — Selector

cell array

Selector, specified as the comma-separated pair consisting of 'Selector' and a cell array containing a function handle and one or more attribute names. The function must return a logical scalar. Use the Selector parameter to import only features for which the function, when applied to the corresponding attribute values, returns true. For more information about function handles, see “Create Function Handle” (MATLAB).

Attributes — Attribute names

cell array

Attribute names, specified as the comma-separated pair consisting of 'Attributes' and a cell array of attribute names. Use the parameter Attributes to include listed attributes and set the order of attributes in the structure array. Use {} to omit all attributes.

UseGeoCoords — Flag to return shapefile contents in a geostruct

false (default) | true

Flag to return shapefile contents in a geostruct, specified as the comma-separated pair consisting of 'UseGeoCoords' and false or true.

When UseGeoCoords is set to true, the shapefile contents are returned in a geostruct. Use this parameter when you know that the x- and y- coordinates in the shapefile actually represent longitude and latitude data. If you do not know whether you are working with geographic or map coordinates, see “Mapstructs and Geostructs”.

Output Arguments

S — Vector geographic features

N-by-1 geographic data structure array

Vector geographic features, returned as an N -by-1 map geographic data structure array. Unless `UseGeoCoords` is `true`, `S` is a `mapstruct` and contains an element for each non-null, spatial feature in the shapefile.

A — Feature attribute information

N -by-1 attribute structure array

Feature attribute information, returned as an N -by-1 attribute structure array corresponding to array `S`.

The fields in the output structure arrays `S` and `A` depend on the type of shape contained in the file and the names and types of attributes included in the file. The `shaperead` function supports the following four attribute types: `numeric` and `floating` (stored as type `double` in MATLAB) and `character` and `date` (stored as `char` array).

See Also

`shapeinfo` | `shapewrite`

Topics

“Geographic Data Structures”

“Find Geospatial Data Online”

Introduced before R2006a

shapewrite

Write geographic vector data structure to shapefile

Syntax

```
shapewrite(S,filename)
shapewrite(S,filename,'DbfSpec',dbfspec)
```

Description

`shapewrite(S,filename)` writes the vector geographic features stored in shapefile `S` to the file specified by `filename` in shapefile format.

`shapewrite(S,filename,'DbfSpec',dbfspec)` writes a shapefile in which the content and layout of the DBF file is controlled by `dbfspec`, a DBF specification.

Examples

Write Feature Data to Shapefile

Derive a shapefile from `concord_roads.shp` in which roads of CLASS 5 and greater are omitted.

Get information about the contents of a shapefile. Note that it contains 609 features (`NumFeatures`).

```
shapeinfo('concord_roads')

ans =
    Filename: [3x67 char]
    ShapeType: 'PolyLine'
    BoundingBox: [2x2 double]
    NumFeatures: 609
    Attributes: [5x1 struct]
```

Read a selection of the data in the file into a mapstruct. Note the use of the 'Selector' option in shaperead, together with an anonymous function, to read only the main roads from the original shapefile.

```
S = shaperead('concord_roads','Selector', ...
             {@(roadclass) roadclass < 4, 'CLASS'});
```

Write the data to a new shapefile.

```
shapewrite(S,'main_concord_roads.shp')
```

Get information about the contents of the new shapefile.

```
shapeinfo('main_concord_roads') % 107 features
```

```
ans =
    Filename: [3x24 char]
    ShapeType: 'PolyLine'
    BoundingBox: [2x2 double]
    NumFeatures: 107
    Attributes: [5x1 struct]
```

Write Data Stored in mappoint to Shapefile

Read a shapefile containing a vector of world cities and store the data in a mappoint vector.

```
p = mappoint(shaperead('worldcities.shp'))
```

```
p =
```

```
318x1 mappoint vector with properties:
```

```
Collection properties:
  Geometry: 'point'
  Metadata: [1x1 struct]
Feature properties:
  X: [1x318 double]
  Y: [1x318 double]
  Name: {1x318 cell}
```

Append Paderborn Germany to the mappoint vector. Note that the size of p has increased by 1.

```
x = 51.715254;
y = 8.75213;
p = append(p,x,y, 'Name', 'Paderborn')

p =

319x1 mappoint vector with properties:

Collection properties:
    Geometry: 'point'
    Metadata: [1x1 struct]
Feature properties:
    X: [1x319 double]
    Y: [1x319 double]
    Name: {1x319 cell}
```

Write the updated mappoint vector to a shapefile.

```
shapewrite(p, 'worldcities_updated')
```

Input Arguments

S — Vector geographic features

mappoint vector | mapshape vector | mapstruct vector | geopoint vector | geoshape vector | geostruct

Vector geographic features, specified as a mappoint vector, mapshape vector, mapstruct (with X and Y coordinate fields), geopoint vector, geoshape vector, or a geostruct (with 'Lat' and 'Lon' fields). A has the following restrictions on its attribute fields:

- Each attribute field value must be either a real, finite, scalar double or a character vector.
- The type of a given attribute must be consistent across all features.
- If S is a geopoint vector, geoshape vector, or a geostruct, shapewrite writes the latitude and longitude values as Y and X coordinates, respectively.
- If a given attribute is integer-valued for all features, shapewrite writes it to the [basename ' .dbf'] file as an integer. If an attribute is non-integer-valued for any feature, shapewrite writes it as a fixed point decimal value with six digits to the right of the decimal place.

filename — File name

string scalar | character vector

File name and location of the shapefile to create, specified as a string scalar or character vector. If the file name includes a file extension, it must be `'.shp'` or `'.SHP'`. `shapewrite` creates three output files: `[basename '.shp']`, `[basename '.shx']`, and `[basename '.dbf']`, where `basename` is `filename` without its extension.

dbfspec — Feature attributes to include in shapefile

scalar structure

Feature attributes to include in the shapefile, specified as a scalar MATLAB structure containing one field for each feature attribute. Assign to that field a scalar structure with the following four fields:

- `FieldName` — The field name to be used in the file
- `FieldType` — The field type to be used in the file: `'N'` (numeric) or `'C'` (character)
- `FieldLength` — The field length in the file, in bytes
- `FieldDecimalCount` — For numeric fields, the number of digits to the right of the decimal place

To create a DBF spec, call `makedbfspec` and then modify the output to remove attributes or change the `FieldName`, `FieldLength`, or `FieldDecimalCount` for one or more attributes.

To include an attribute in the output file, specify a field in `dbfspec` with the same name as the attribute is specified in `S`.

Tips

- The `xBASE` (`.dbf`) file specifications require that `geostruct` and `mapstruct` attribute names are truncated to 11 characters when copied as DBF field names. Consider shortening long field names before calling `shapewrite`. By doing this, you make field names in the DBF file more readable and avoid introducing duplicate names as a result of truncation.
- Remember to set your character encoding scheme to match that of the geographic data structure you are exporting. For instance, if you are exporting a map that displays Japanese text, configure your machine to support `Shift-JIS` character encoding.

See Also

madebfspec | shapeinfo | shaperead

Topics

“Geographic Data Structures”

Introduced before R2006a

showaxes

Toggle display of map coordinate axes

Syntax

```
showaxes(action)  
showaxes
```

Description

`showaxes(action)` modifies the Cartesian axes based on the value of *action*, as defined in the Inputs section below.

`showaxes` toggles between displaying the default axes ticks on the MATLAB Cartesian axes and removing the axes ticks.

Input Arguments

action

A character vector or RGB triple that specifies how to modify the Cartesian axes

Default:

| Value | Action |
|----------|--|
| 'on' | Displays the MATLAB Cartesian axes and default axes ticks |
| 'off' | Removes the axes ticks from the MATLAB Cartesian axes |
| 'hide' | Hides the Cartesian axes |
| 'show' | Shows the Cartesian axes |
| 'reset' | Sets the Cartesian axes to the default settings |
| 'boxoff' | Removes axes ticks, color, and box from the Cartesian axes |

| Value | Action |
|-----------------|---|
| <i>colorstr</i> | Sets the Cartesian axes to the color specified by <i>colorstr</i> |
| <i>colorvec</i> | Uses <i>colorvec</i> to set the Cartesian axes color |

See Also

axesm

Introduced before R2006a

showm

Specify graphic objects to display on map axes

Syntax

```
showm  
showm(handle)  
showm(object)
```

Description

showm brings up a dialog box for selecting the objects to show (set their `Visible` property to 'on').

showm(handle) shows the objects specified by a vector of handles.

showm(object) shows those objects specified by the *object* character vector, which can be any character vector recognized by the `handlem` function.

See Also

clma | clmo | handlem | hidem | namem | tagm

Introduced before R2006a

size

Return size of geographic or planar vector

Syntax

```
sz = size(v)
sz = size(v,dim)
[m, n] = size(v)
```

Description

`sz = size(v)` returns the vector `[length(v), 1]`.

`sz = size(v,dim)` returns the length of geographic or planar vector `v` in the dimension specified by `dim`.

`[m, n] = size(v)` returns the length of `v` for `m` and 1 for `n`.

Examples

Find the Size of a Mapshape Vector

Create a mapshape vector from a `structArray`.

```
structArray = shaperead('worlddrivers');
ms = mapshape(structArray)

ms =
    128x1 mapshape vector with properties:

    Collection properties:
        Geometry: 'line'
        Metadata: [1x1 struct]
    Vertex properties:
        (128 features concatenated with 127 delimiters)
```

```

        X: [1x5542 double]
        Y: [1x5542 double]
Feature properties:
    Name: {1x128 cell}

```

Get the size of the mapshape vector.

```
sz = size(ms)
```

```
sz = 1x2
```

```
    128     1
```

Input Arguments

v — Geographic or planar vector

geopoint, geoshape, mappoint, or mapshape object

Geographic or planar vector, specified as a `geopoint`, `geoshape`, `mappoint`, or `mapshape` object.

dim — Dimension to measure length

positive integer scalar

Dimension to measure length of vector `v`, specified as a positive integer scalar.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64` | `logical`

Output Arguments

sz — Size of geographic or planar vector

nonnegative integer scalar or two-element vector

Size of vector `v`, returned as a nonnegative integer scalar or a two-element vector.

- When `dim` is not specified, `sz` is the two-element vector `[length(v), 1]`.

- When `dim` is 1, `sz` is a scalar equal to the length of `v`.
- When `dim` \geq 2, `sz` is 1.

Data Types: `double`

m — Size of vector in first dimension

nonnegative integer scalar

Size of vector `v` in the first dimension, returned as a nonnegative integer scalar. `m` is `length(v)`.

Data Types: `double`

n — Size of vector in second dimension

1

Size of vector `v` in the second dimension, returned as the value 1.

Data Types: `double`

See Also

`length`

Introduced in R2012a

sizem

Row and column dimensions needed for regular data grid

Note `sizem` is not recommended and may be removed in a future release. Instead, use `georefcells` to construct a geographic raster reference object and then access its `RasterSize` property:

```
R = georefcells(latlim,lonlim,1/scale,1/scale);  
nrows = R.RasterSize(1);  
ncols = R.RasterSize(2);
```

Syntax

```
[r,c] = sizem(latlim,lonlim,scale)  
rc = sizem(latlim,lonlim,scale)  
[r,c,refvec] = sizem(latlim,lonlim,scale)
```

Description

`[r,c] = sizem(latlim,lonlim,scale)` returns the required size for a regular data grid lying between the latitude and longitude limits specified by the two-element input vectors `latlim` and `lonlim`, which are of the form [`south-limit north-limit`] and [`west-limit east-limit`], respectively. The `scale` is the desired cells-per-degree measure of the desired data grid.

`rc = sizem(latlim,lonlim,scale)` returns the size of the matrix in one two-element vector.

`[r,c,refvec] = sizem(latlim,lonlim,scale)` also returns the three-element referencing vector geolocating the desired regular data grid.

Examples

How large a matrix would be required for a map of the world at a scale of 25 matrix cells per degree? (That's $25 \times 25 = 625$ cells per “square” degree.)

```
[r,c] = size([90,-90],[-180,180],25)
```

```
r =  
    4500
```

```
c =  
    9000
```

Bear in mind for memory purposes — $9000 \times 4500 = 4.05 \times 10^7$ entries!

See Also

[findm](#) | [limitm](#) | [nanm](#) | [onem](#) | [spzeros](#) | [zeros](#)

Introduced before R2006a

sizesMatch

Package: map.rasterref

Determine if geographic or map raster object and image or raster are size-compatible

Syntax

```
tf = sizesMatch(R,A)
```

Description

`tf = sizesMatch(R,A)` determines whether geographic or map raster R is size-compatible with image or raster A.

Examples

Check If Image and Geographic Raster Are Size-Compatible

Create a GeographicPostingsReference raster reference object.

```
latlim = [0 90];  
lonlim = [-180 180];  
rasterSize = [91 361];  
R = georefpostings(latlim,lonlim,rasterSize, 'ColumnsStartFrom', 'north')
```

R =

GeographicPostingsReference with properties:

```
LatitudeLimits: [0 90]  
LongitudeLimits: [-180 180]  
RasterSize: [91 361]  
RasterInterpretation: 'postings'  
ColumnsStartFrom: 'north'  
RowsStartFrom: 'west'  
SampleSpacingInLatitude: 1
```

```
SampleSpacingInLongitude: 1
RasterExtentInLatitude: 90
RasterExtentInLongitude: 360
  XIntrinsicLimits: [1 361]
  YIntrinsicLimits: [1 91]
CoordinateSystemType: 'geographic'
  AngleUnit: 'degree'
```

Create an arbitrary image (raster) with dimensions 91-by-361. Confirm that the image size is compatible with the geographic raster reference object.

```
A = ones(91,361);
tf_A = sizesMatch(R,A)

tf_A = logical
      1
```

Create an image of a different size. Confirm that this new image is not size-compatible with the geographic raster reference object.

```
B = ones(90,361);
tf_B = sizesMatch(R,B)

tf_B = logical
      0
```

Input Arguments

R — Geographic or map raster

GeographicCellsReference object | GeographicPostingsReference object | MapCellsReference object | MapPostingsReference object

Geographic or map raster, specified as a GeographicCellsReference, GeographicPostingsReference, MapCellsReference, or MapPostingsReference object.

A — Image or raster

numeric array or raster object

Image or raster, specified as a numeric array or raster object.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64` | `logical` | geographic raster object | map raster object

Output Arguments

tf — Flag indicating geographic or map raster is size-compatible with image or raster

logical scalar

Flag indicating geographic or map raster is size-compatible with image or raster, returned as a logical scalar. `tf` is `True` when `R.RasterSize` is equal to `[size(A,1) size(A,2)]` or `A.RasterSize`.

Data Types: `logical`

See Also

Introduced in R2013b

sm2deg

Convert spherical distance from statute miles to degrees

Syntax

```
deg = sm2deg(sm)
deg = sm2deg(sm, radius)
deg = sm2deg(sm, sphere)
```

Description

`deg = sm2deg(sm)` converts distances from statute miles to degrees, as measured along a great circle on a sphere with a radius of 3958.748 sm, the mean radius of the Earth.

`deg = sm2deg(sm, radius)` converts distances from statute miles to degrees, as measured along a great circle on a sphere having the specified radius.

`deg = sm2deg(sm, sphere)` converts distances from statute miles to degrees, as measured along a great circle on a sphere approximating an object in the Solar System.

Input Arguments

sm — Distance in statute miles

numeric array

Distance in statute miles, specified as a numeric array.

Data Types: `single` | `double`

radius — Radius

3958.748 (default) | numeric scalar

Radius of sphere in units of statute miles, specified as a numeric scalar.

sphere — Sphere

'sun' | 'moon' | 'mercury' | 'venus' | 'earth' | ...

Sphere approximating an object in the Solar System, specified as one of the following values: 'sun', 'moon', 'mercury', 'venus', 'earth', 'mars', 'jupiter', 'saturn', 'uranus', 'neptune', or 'pluto'. The value of sphere is case-insensitive.

Output Arguments

deg — Distance in degrees

numeric array

Distance in degrees, returned as a numeric array.

Data Types: `single` | `double`

See Also

`deg2rad` | `deg2sm` | `km2deg` | `nm2deg` | `rad2deg` | `sm2rad`

Introduced in R2007a

sm2km

Convert statute miles to kilometers

Syntax

`km = sm2km(sm)`

Description

`km = sm2km(sm)` converts distances from statute miles to kilometers.

See Also

`deg2km` | `deg2nm` | `deg2sm` | `deg2sm` | `km2deg` | `km2rad` | `nm2deg` | `nm2rad` | `rad2km` | `rad2nm` | `rad2sm` | `sm2deg` | `sm2rad`

Introduced in R2007a

sm2nm

Convert statute to nautical miles

Syntax

```
nm = sm2nm(sm)
```

Description

nm = sm2nm(sm) converts distances from statute to nautical miles.

See Also

deg2km | deg2nm | deg2sm | deg2sm | km2deg | km2rad | nm2deg | nm2rad | rad2km | rad2nm | rad2sm | sm2deg | sm2rad

Introduced in R2007a

sm2rad

Convert spherical distance from statute miles to radians

Syntax

```
rad = sm2rad(sm)
rad = sm2rad(sm, radius)
rad = sm2rad(sm, sphere)
```

Description

`rad = sm2rad(sm)` converts distances from statute miles to radians, as measured along a great circle on a sphere with a radius of 3958.748 sm, the mean radius of the Earth.

`rad = sm2rad(sm, radius)` converts distances from statute miles to radians, as measured along a great circle on a sphere having the specified radius.

`rad = sm2rad(sm, sphere)` converts distances from statute miles to radians, as measured along a great circle on a sphere approximating an object in the Solar System.

Input Arguments

sm — Distance in statute miles

numeric array

Distance in statute miles, specified as a numeric array.

Data Types: `single` | `double`

radius — Radius

3958.748 (default) | numeric scalar

Radius of sphere in units of statute miles, specified as a numeric scalar.

sphere — Sphere

'sun' | 'moon' | 'mercury' | 'venus' | 'earth' | ...

Sphere approximating an object in the Solar System, specified as one of the following values: 'sun', 'moon', 'mercury', 'venus', 'earth', 'mars', 'jupiter', 'saturn', 'uranus', 'neptune', or 'pluto'. The value of sphere is case-insensitive.

Output Arguments

rad — Distance in radians

numeric array

Distance in radians, returned as a numeric array.

Data Types: `single` | `double`

See Also

`deg2rad` | `km2rad` | `nm2rad` | `rad2deg` | `rad2sm` | `sm2deg`

Introduced in R2007a

smoothlong

Remove discontinuities in longitude data

Note The `smoothlong` function is obsolete and has been replaced by `unwrapMultipart`, which requires input to be in radians. When working in degrees, use `rad2deg(unwrapMultipart(deg2rad(lon)))`.

Syntax

```
ang = smoothlong(angin)
ang = smoothlong(angin, angleunits)
```

Description

`ang = smoothlong(angin)` removes discontinuities in longitude data. The resulting angles can cover more than one revolution.

`ang = smoothlong(angin, angleunits)` uses the units defined by *angleunits*. If omitted, default units of 'degrees' are assumed. Valid *angleunits* are:

- 'degrees' — decimal degrees
- 'radians'

See Also

`unwrapMultipart`

Introduced before R2006a

spcread

Read columns of data from ASCII text file

Syntax

```
mat = spcread
mat = spcread(filename)
mat = spcread(cols)
```

Description

`mat = spcread` reads an ASCII file of space-delimited data in two columns and returns the data in a matrix, `mat`. The file is selected by dialog box.

`mat = spcread(filename)` specifies the file from which to read by its name, given as the character vector *filename*.

`mat = spcread(cols)` specifies the number of columns of space-delimited data in the file with the integer `cols`. The default value of `cols` is 2.

Tips

The `spcread` function is similar to the standard MATLAB function `dlmread`. `spcread`, however, is much faster at reading large data sets of the type common for geographic purposes.

See Also

`nanclip`

Introduced before R2006a

spzerom

Construct sparse regular data grid of 0s

Note `spzerom` is not recommended and may be removed in a future release. Instead, use `georefcells` to construct a geographic raster reference object and then use `sparse` to initialize a data grid of the appropriate size:

```
R = georefcells(latlim,lonlim,1/scale,1/scale);  
Z = sparse(R.RasterSize(1),R.RasterSize(2));
```

Syntax

```
[Z,refvec] = spzerom(latlim,lonlim,scale)
```

Description

`[Z,refvec] = spzerom(latlim,lonlim,scale)` returns a sparse regular data grid consisting entirely of 0s and a three-element referencing vector for the returned Z. The two-element vectors `latlim` and `lonlim` define the latitude and longitude limits of the geographic region. They should be of the form `[south north]` and `[west east]`, respectively. The scalar `scale` specifies the number of rows and columns per degree of latitude and longitude.

Examples

```
[Z,refvec] = spzerom([46,51],[-79,-75],1)
```

```
Z =  
    All zero sparse: 5-by-4  
refvec =  
     1     51    -79
```

See Also

limitm | nanm | onem | sizem | zerom

Introduced before R2006a

stdist

Standard distance for geographic points

Syntax

```
dist = stdist(lat,lon)
dist = stdist(lat,lon,units)
dist = stdist(lat,lon,ellipsoid)
dist = stdist(lat,lon,ellipsoid,units,method)
```

Description

`dist = stdist(lat,lon)` computes the average standard distance for geographic data. This function assumes that the data is distributed on a sphere. In contrast, `std` assumes that the data is distributed on a Cartesian plane. The result is a single value based on the great-circle distance of the data points from their geographic mean point. When `lat` and `lon` are vectors, a single distance is returned. When `lat` and `lon` are matrices, a row vector of distances is given, providing the distances for each column of `lat` and `lon`. N-dimensional arrays are not allowed. Distances are returned in degrees of angle units.

`dist = stdist(lat,lon,units)` indicates the angular units of the data. When the standard angle units is omitted, 'degrees' is assumed. Output measurements are in terms of these `units` (as arc length distance).

`dist = stdist(lat,lon,ellipsoid)` specifies the shape of the Earth to be used with `ellipsoid`, which can be a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form [`semimajor_axis` `eccentricity`]. The default is a unit sphere. Output measurements are in terms of the distance units of the semimajor axis of the `ellipsoid`.

`dist = stdist(lat,lon,ellipsoid,units,method)` specifies the method of calculating the standard distance of the data. The default, 'linear', is simply the average great circle distance of the data points from the centroid. Using 'quadratic' results in the square root of the average of the squared distances, and 'cubic' results in the cube root of the average of the cubed distances.

Background

The function `stdm` provides independent standard deviations in latitude and longitude of data points. `stdist` provides a means of examining data scatter that does not separate these components. The result is a *standard distance*, which can be interpreted as a measure of the scatter in the great circle distance of the data points from the centroid as returned by `meanm`.

The output distance can be thought of as the radius of a circle centered on the geographic mean position, which gives a measure of the spread of the data.

Examples

Create latitude and longitude lists using the `worldcities` data set and obtain standard distance deviation for group (compare with the example for `stdm`):

```
cities = shaperead('worldcities.shp', 'UseGeoCoords', true);
Paris = strcmp('Paris', {cities(:).Name});
London = strcmp('London', {cities(:).Name});
Rome = strcmp('Rome', {cities(:).Name});
Madrid = strcmp('Madrid', {cities(:).Name});
Berlin = strcmp('Berlin', {cities(:).Name});
Athens = strcmp('Athens', {cities(:).Name});
lat = [cities(Paris).Lat cities(London).Lat...
       cities(Rome).Lat cities(Madrid).Lat...
       cities(Berlin).Lat cities(Athens).Lat]
lon = [cities(Paris).Lon cities(London).Lon...
       cities(Rome).Lon cities(Madrid).Lon...
       cities(Berlin).Lon cities(Athens).Lon]

dist = stdist(lat, lon)

lat =
    48.8708    51.5188    41.9260    40.4312    52.4257    38.0164
lon =
     2.4131    -0.1300    12.4951    -3.6788    13.0802    23.5183
dist =
     8.1827
```

See Also

meanm | stdm

Introduced before R2006a

stdm

Standard deviation for geographic points

Syntax

```
[latdev,londev] = stdm(lat,lon)
[latdev,londev] = stdm(lat,lon,ellipsoid)
[latdev,londev] = stdm(lat,lon,units)
```

Description

`[latdev,londev] = stdm(lat,lon)` returns row vectors of the latitude and longitude geographic standard deviations for the data points specified by the columns of `lat` and `lon`.

`[latdev,londev] = stdm(lat,lon,ellipsoid)` specifies the shape of the Earth to be used by the `ellipsoid`, which can be a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. The default `ellipsoid` is a unit sphere. Output measurements are in terms of the distance units of the `ellipsoid` vector.

`[latdev,londev] = stdm(lat,lon,units)` indicates the angular units of the data. When you omit `units`, 'degrees' is assumed. Output measurements are in terms of these units (as arc length distance).

If a single output argument is used, then `geodevs = [latdev longdev]`. This is particularly useful if the original `lat` and `lon` inputs are column vectors.

Background

Determining the deviations of geographic data in latitude and longitude is more complicated than simple sum-of-squares deviations from the data averages. For latitude deviation, a straightforward angular standard deviation calculation is performed from the *geographic mean* as calculated by `meanm`. For longitudes, a similar calculation is

performed based on data *departure* rather than on angular deviation. See “Geographic Statistics for Point Locations on a Sphere” in the *Mapping Toolbox User's Guide*.

Examples

Create latitude and longitude lists using the `worldcities` data set and obtain standard distance deviation for group (compare with the example for `stdist`):

```
cities = shaperead('worldcities.shp', 'UseGeoCoords', true);
Paris = strcmp('Paris',{cities(:).Name});
London = strcmp('London',{cities(:).Name});
Rome = strcmp('Rome',{cities(:).Name});
Madrid = strcmp('Madrid',{cities(:).Name});
Berlin = strcmp('Berlin',{cities(:).Name});
Athens = strcmp('Athens',{cities(:).Name});
lat = [cities(Paris).Lat cities(London).Lat...
       cities(Rome).Lat cities(Madrid).Lat...
       cities(Berlin).Lat cities(Athens).Lat]
lon = [cities(Paris).Lon cities(London).Lon...
       cities(Rome).Lon cities(Madrid).Lon...
       cities(Berlin).Lon cities(Athens).Lon]
[latstd,lonstd]=stdm(lat,lon)
```

```
lat =
    48.8708    51.5188    41.9260    40.4312    52.4257    38.0164
lon =
     2.4131    -0.1300    12.4951    -3.6788    13.0802    23.5183
latstd =
     2.7640
lonstd =
    68.7772
```

See Also

`departure` | `filterm` | `hista` | `histr` | `meanm` | `stdist`

Introduced before R2006a

stem3m

Project stem plot on map axes

Syntax

```
h = stem3m(lat,lon,z)
h = stem3m(lat,lon,z,LineStyle)
h = stem3m(lat,lon,z,PropertyName,PropertyValue,...)
```

Description

`h = stem3m(lat,lon,z)` displays a stem plot on the current map axes. Stems are located at the points (lat,lon) and extend from an altitude of 0 to the values of z . The coordinate inputs should be in the same `AngleUnits` as the map axes. It is important to note that the selection of z -values will greatly affect the 3-D look of the plot. Regardless of `AngleUnits`, the x and y limits of the map axes are at most $-\pi$ to $+\pi$ and $-\pi/2$ to $+\pi/2$, respectively. This means that for most purposes, appropriate z values would be on the order of 1 to 3, not 10 to 30. The axes `DataAspectRatio` property can be used to adjust the appearance of the graphic. The handles of the displayed stem lines can be returned in `h`.

`h = stem3m(lat,lon,z,LineStyle)` defines the style of the stem plot's lines, specified by a `linespec`.

`h = stem3m(lat,lon,z,PropertyName,PropertyValue,...)` allows any property/value pair recognized by the MATLAB `line` function to be specified for the stems.


A stem plot displays data as lines extending normal to the xy -plane, in this case, on a map.

Examples

Project Stem Plot on Map Axes

Project a stem plot on a map axes.

```
load coastlines
axesm sinusoid;
view(3)
h = framem;
set(h,'zdata',zeros(size(coastlat)))
plotm(coastlat,coastlon)
ptlat = [0 30 30 -50 -78]';
ptlon = [0 30 -70 65 -35]';
ptz = [1 1.5 2 .5 1]';
stem3m(ptlat,ptlon,ptz,'r-')
```



See Also

scatterm

Introduced before R2006a

str2angle

Convert text to angles in degrees

Syntax

```
angles = str2angle(strings)
```

Description

`angles = str2angle(strings)` converts string scalars or character vectors containing latitudes or longitudes, expressed in one of four different formats of degree-minutes-seconds, to numeric angles in units of degrees.

| Format | Description | Example |
|-------------------------------------|-------------|-----------------|
| Degree Symbol, Single/Double Quotes | | '123°30' '00"W' |
| 'd', 'm', 's' Separators | | '123d30m00sW' |
| Minus Signs as Separators | | '123-30-00W' |
| "Packed DMS" | | '1233000W' |

Input must conform closely to the examples provided; in particular, the seconds field must be included, even if it is not significant. Except in Packed DMS format, the seconds field can contain a fractional component. Sign characters are not supported. Instead, terminate each value with 'N' for positive latitude, 'S' for negative latitude, 'E' for positive longitude, or 'W' for negative longitude. `strings` is a string scalar, character vector, or a cell array of character vectors. For backward compatibility, `strings` can also be a character matrix. If more than one angle is represented, `strings` can either contain homogeneous or heterogeneous formatting (see example). `angles` is a column vector of class `double`.

Examples

```
strs = {'23°30' '00"N', '23-30-00S', '123d30m00sE', '1233000W'}
```

```
strs =  
    '23°30'00"N'    '23-30-00S'    '123d30m00sE'    '1233000W'  
  
str2angle(strs)  
  
ans =  
    23.5  
   -23.5  
   123.5  
  -123.5
```

See Also

angl2str

Introduced before R2006a

struct

Convert geographic or planar vector to scalar structure

Syntax

```
s = struct(v)
```

Description

`s = struct(v)` converts the geographic or planar vector `v` to a scalar structure, `s`.

Examples

Convert a Mappoint Vector into a Structure

Create a mappoint vector.

```
mp = mappoint(shaperead('tsunamis'))
```

```
mp =  
162x1 mappoint vector with properties:
```

```
Collection properties:  
    Geometry: 'point'  
    Metadata: [1x1 struct]  
Feature properties:  
    X: [1x162 double]  
    Y: [1x162 double]  
    Year: [1x162 double]  
    Month: [1x162 double]  
    Day: [1x162 double]  
    Hour: [1x162 double]  
    Minute: [1x162 double]  
    Second: [1x162 double]  
    Val_Code: [1x162 double]
```

```
Validity: {1x162 cell}
Cause_Code: [1x162 double]
Cause: {1x162 cell}
Eq_Mag: [1x162 double]
Country: {1x162 cell}
Location: {1x162 cell}
Max_Height: [1x162 double]
Iida_Mag: [1x162 double]
Intensity: [1x162 double]
Num_Deaths: [1x162 double]
Desc_Deaths: [1x162 double]
```

Convert the mappoint vector into a structure.

```
s = struct(mp)
```

```
s = struct with fields:
  Geometry: 'point'
  Metadata: [1x1 struct]
    X: [1x162 double]
    Y: [1x162 double]
    Year: [1x162 double]
    Month: [1x162 double]
    Day: [1x162 double]
    Hour: [1x162 double]
    Minute: [1x162 double]
    Second: [1x162 double]
  Val_Code: [1x162 double]
  Validity: {1x162 cell}
  Cause_Code: [1x162 double]
  Cause: {1x162 cell}
  Eq_Mag: [1x162 double]
  Country: {1x162 cell}
  Location: {1x162 cell}
  Max_Height: [1x162 double]
  Iida_Mag: [1x162 double]
  Intensity: [1x162 double]
  Num_Deaths: [1x162 double]
  Desc_Deaths: [1x162 double]
```

Input Arguments

v — Geographic or planar vector

geopoint, geoshape, mappoint, or mapshape object

Geographic or planar vector, specified as a `geopoint`, `geoshape`, `mappoint`, or `mapshape` object.

Output Arguments

s — Structure representing a geographic or planar vector

scalar structure

Structure representing a geographic or planar vector, returned as a scalar structure.

See Also

`properties`

Introduced in R2012a

surfacem

Project and add geolocated data grid to current map axes

Syntax

```
surfacem(lat, lon, Z)
surfacem(latlim, lonlim, Z)
surfacem(lat, lon, Z, alt)
surfacem(..., prop1, val1, prop2, val2, ...)
h = surfacem(...)
```

Description

`surfacem(lat, lon, Z)` constructs a surface to represent the data grid `Z` in the current map axes. The surface lies flat in the horizontal plane with its `CData` property set to `Z`. The vectors or 2-D arrays `lat` and `lon` define the latitude-longitude graticule mesh on which `Z` is displayed. For a complete description of the various forms that `lat` and `lon` can take, see `surfm`.

`surfacem(latlim, lonlim, Z)` defines the graticule using the latitude and longitude limits `latlim` and `lonlim`. These limits should match the geographic extent of the data grid `Z`. The two-element vector `latlim` has the form:

```
[southern_limit northern_limit]
```

Likewise, `lonlim` has the form:

```
[western_limit eastern_limit]
```

A latitude-longitude graticule of size 50-by-100 is constructed. The surface `FaceColor` property is `'texturemap'`, except when `Z` is precisely 50-by-100, in which case it is `'flat'`.

`surfacem(lat, lon, Z, alt)` sets the `ZData` property of the surface to `'alt'`, resulting in a 3-D surface. `lat` and `lon` must result in a graticule mesh that matches `alt` in size. `CData` is set to `Z`. `Facecolor` is `'texturemap'`, unless `Z` matches `alt` in size, in which case it is `'flat'`.

`surfaced(...,prop1,val1,prop2,val2,...)` applies additional MATLAB graphics properties to the surface via property/value pairs. You can specify any property accepted by the surface function, except `XData`, `YData`, and `ZData`.


`h = surfaced(...)` returns a handle to the surface object.

Note Unlike `meshm` and `surfm`, `surfaced` always adds a surface to the current axes, regardless of hold state.

Examples

Construct a surface to represent the data grid `topo`.

```
figure('Color','white')
    load topo
    latlim = [-90 90];
    lonlim = [ 0 360];
    gratsize = 1 + [diff(latlim), diff(wrapTo360(lonlim))]/6;
    [lat, lon] = meshgrat(latlim, lonlim, gratsize);
    worldmap world
    surfaced(lat, lon, topo)
    demcmap(topo)
```



See Also

geoshow | meshm | pcolor | surfm

Introduced before R2006a

surflm

3-D shaded surface with lighting on map axes

Syntax

```
surflm(lat,lon,Z)
surflm(latlim,lonlim,Z)
surflm(...,s)
surflm(...,s,k)
h = surflm(...)
```

Description

`surflm(lat,lon,Z)` and `surflm(latlim,lonlim,Z)` are the same as `surfm(...)` except that they highlight the surface with a light source. The default light source (45 degrees counterclockwise from the current view) and reflectance constants are the same as in `surfl`.

`surflm(...,s)` and `surflm(...,s,k)` use a light source vector, `s`, and a vector of reflectance constants, `k`. For more information on `s` and `k`, see the help for `surfl`.

`h = surflm(...)` returns a handle to the surface object.


Examples

Project 3-D Shaded Surface with Lighting on Map Axes

Project a 3-D shaded surface with lighting on the current map axes. Note that in the following example, the graticule is the size of `topo` (180 x 360) and is rendered in 3-D, so it might take a while. It is also memory intensive.

```
figure('Color','white')
load topo
axesm miller
```

```
axis off;  
framem on;  
gridm on;  
[lat,lon] = meshgrat(topo,topolegend);  
surflm(lat,lon,topo)  
colormap(gray)  
load coastlines  
plotm(coastlat,coastlon,max(topo(:)),...  
      'LineWidth',1.5,'Color','yellow')
```



Tips

`surf ℓ m` is like `surf m` , except that it shades the monochrome map surface with a light source, and the only allowed graticule is the size of the data matrix.

See Also

`surf m`

Introduced before R2006a

surflsrm

3-D lighted shaded relief of geolocated data grid

Syntax

```
surflsrm(lat, long, Z)
surflsrm(lat, long, Z, [azim elev])
surflsrm(lat, long, Z, [azim elev], cmap)
surflsrm(lat, long, Z, [azim elev], cmap, clim)
h = surflsrm(...)
```

Description

`surflsrm(lat, long, Z)` displays the geolocated data grid, colored according to elevation and surface slopes. The current axes must have a valid map projection definition.

`surflsrm(lat, long, Z, [azim elev])` displays the geolocated data grid with the light coming from the specified azimuth and elevation. Lighting is applied before the data is projected. Angles are in degrees, with the azimuth measured clockwise from North, and elevation up from the zero plane of the surface. By default, the direction of the light source is east (90° azimuth) at an elevation of 45° .

`surflsrm(lat, long, Z, [azim elev], cmap)` displays the geolocated data grid using the provided colormap. The number of grayscales is chosen to keep the size of the shaded colormap below 256. By default, the colormap is constructed from 16 colors and 16 grays. If the vector of azimuth and elevation is empty, the default locations are used.


`surflsrm(lat, long, Z, [azim elev], cmap, clim)` uses the provided color axis limits, which are, by default, automatically computed from the data.

`h = surflsrm(...)` returns the handle to the surface drawn.

Examples

Create a new colormap using `demcmap` with white colors for the sea and default colors for land. Use this colormap for the lighted shaded relief map of the Middle East region:

```
load mapmtx  
[cmap,clim] = demcmap(map1,[],[1 1 1],[]);  
axesm loximuth  
surflsrm(lt1,lg1,map1,[],cmap,clim)
```



Tips

This function effectively multiplies two colormaps, one with color based on elevation, the other with a grayscale based on the slope of the surface, to create a new colormap. This produces an effect similar to using a light on a surface, but with all of the visible colors actually in the colormap. Lighting calculations are performed on the unprojected data.

See Also

[meshlsrn](#) | [meshm](#) | [pcolorm](#) | [shaderel](#) | [surfacem](#) | [surflm](#) | [surfm](#)

Introduced before R2006a

surfm

Project geolocated data grid on map axes

Syntax

```
surfm(lat,lon,Z)
surfm(latlim,lonlim,Z)
surfm(lat,lon,Z,alt)
surfm(...,prop1,val1,prop2,val2,...)
h = surfm(...)
```

Description

`surfm(lat,lon,Z)` constructs a surface to represent the data grid `Z` in the current map axes. The surface lies flat in the horizontal plane with its `CData` property set to `Z`. The 2-D arrays or vectors `lat` and `lon` define the latitude-longitude graticule mesh on which `Z` is displayed. The sizes and shapes of `lat` and `lon` affect their interpretation, and also determine whether the default `FaceColor` property of the surface is `'flat'` or `'texturemap'`. There are three options:

- 2-D arrays (matrices) having the same size as `Z`. `lat` and `lon` are treated as geolocation arrays specifying the precise location of each vertex. `FaceColor` is `'flat'`.
- 2-D arrays having a different size than `Z`. The arrays `lat` and `lon` define a graticule mesh that might be either larger or smaller than `Z`. `lat` and `lon` must match each other in size. `FaceColor` is `'texturemap'`.
- Vectors having more than two elements. The elements of `lat` and `lon` are repeated to form a graticule mesh with size equal to `numel(lat)-by-numel(lon)`. `FaceColor` is `'flat'` if the graticule mesh matches `Z` in size. Otherwise, `FaceColor` is `'texturemap'`.

`surfm` clears the current map if the hold state is `'off'`.

`surfm(latlim,lonlim,Z)` defines the graticule using the latitude and longitude limits `latlim` and `lonlim`, which should match the geographic extent of the data grid `Z`. `Latlim` is a two-element vector of the form:

```
[southern_limit northern_limit]
```

Likewise `lonlim` has the form:

```
[western_limit eastern_limit]
```

A latitude-longitude graticule is constructed to match `Z` in size. The surface `FaceColor` property is `'flat'` by default.

`surfm(lat,lon,Z,alt)` sets the `ZData` property of the surface to `'alt'`, resulting in a 3-D surface. `lat` and `lon` must result in a graticule mesh that matches `alt` in size. `CData` is set to `Z`. The `FaceColor` property is `'texturemap'`, unless `Z` matches `alt` in size, in which case it is `'flat'`.


`surfm(...,prop1,val1,prop2,val2,...)` applies additional MATLAB graphics properties to the surface via property/value pairs. You can specify any property accepted by the surface function except `XData`, `YData`, and `ZData`.

`h = surfm(...)` returns a handle to the surface object.

Examples

Construct a surface to represent the data grid `topo`.

```
figure('Color','white')
load topo
axesm miller
axis off; framem on; gridm on;
[lat,lon] = meshgrat(topo,topolegend,[90 180]);
surfm(lat,lon,topo)
demcmap(topo)
```



Tips

This function warps a data grid to a graticule mesh, which is projected according to the map axes property `MapProjection`. The fineness, or resolution, of this grid determines the quality of the projection and the speed of plotting it. There is no hard and fast rule for sufficient graticule resolution, but in general, cylindrical projections need very few graticule points in the longitudinal direction, while complex curve-generating projections require more.

See Also

`geoshow` | `meshgrat` | `meshm` | `pcolorm` | `surfacem`

Introduced before R2006a

symbolm

Project point markers with variable size

Syntax

```
symbolm(lat,lon,z,'MarkerType')  
symbolm(lat,lon,z,'MarkerType','PropertyName',PropertyValue,...)  
h = symbolm(...)
```

Description

`symbolm(lat,lon,z,'MarkerType')` constructs a thematic map where the symbol size of each data point (`lat`, `lon`) is proportional to its weighting factor (`z`). The point corresponding to `min(z)` is drawn at the default marker size, and all other points are plotted with proportionally larger markers. `MarkerType` is a `LineStyle` specifying a marker and optionally a color.

`symbolm(lat,lon,z,'MarkerType','PropertyName',PropertyValue,...)` applies the line properties to all the symbols drawn.

`h = symbolm(...)` returns a vector of handles to the projected symbols. Each symbol is projected as an individual line object.

See also

`stem3m`, `plotm`, `plot`

Introduced before R2006a

tagm

Set Tag property of map graphics object

Syntax

```
tagm(hndl,tagstr)
```

Description

`tagm(hndl,tagstr)` sets the Tag property of each object designated in the vector of handles `hndl` to the associated row of the character matrix `tagstr`.

This property is recognized by the `namem` and `handlem` functions.

Examples

Normally, a plotted line has a name of 'line':

```
axesm miller  
lats = [3 2 1 1 2 3]; longs = [7 8 9 7 8 9];  
h=plotm(lats,longs);
```

```
untagged = namem(h)  
untagged =  
line
```

The `tagm` function can rename it:

```
tagm(h,'testpath');  
tagged = namem(h)  
tagged =  
testpath
```

See Also

`clma` | `clmo` | `handlem` | `hidem` | `namem` | `showm`

Introduced before R2006a

tbase

Read 5-minute global terrain elevations from TerrainBase

Syntax

```
[Z,refvec] = tbase(scalefactor)
[Z,refvec] = tbase(scalefactor,latlim,lonlim)
```

Description

`[Z,refvec] = tbase(scalefactor)` reads the data for the entire world, reducing the resolution of the data by the specified scale factor. The result is returned as a regular data grid and an associated three-element referencing vector.

`[Z,refvec] = tbase(scalefactor,latlim,lonlim)` reads the data for the part of the world within the latitude and longitude limits. The limits must be two-element vectors in units of degrees.

Background

TerrainBase is a global model of terrain and bathymetry on a regular 5-minute grid (approximately 10 km resolution). It is a compilation of the public domain data from almost 20 different sources, including the DCW-DEM and ETOPO5. The data set was created by the National Geophysical Data Center and World Data Center-A for Solid Earth Geophysics in Boulder, Colorado.

Note For details on locating map data for download over the Internet, see the following documentation at the MathWorks Web site: “Find Geospatial Data Online”.

Examples

Read Data for the Entire World But Read Every 10th Point

Set the scale factor to read every 10th point.

```
scalefactor = 10;
```

Read the data and view the size of the returned variables.

```
[Z,refvec] = tbase(scalefactor);
whos Z refvec
```

| Name | Size | Bytes | Class |
|--------|---------|--------|--------------|
| Z | 216x432 | 746496 | double array |
| refvec | 1x3 | 24 | double array |

Determine the latitude and longitude limits of the geographic quadrangle bounding the data grid.

```
limitm(Z, refvec)
```

```
ans =
```

```

-90      90    -180     180
```

Read Data for a Region at Full Resolution

Set the scale factor to 1 and set the longitude and latitude limits. This example reads the data for Korea and Japan.

```
scalefactor = 1;
latlim = [30 45];
lonlim = [115 145];
```

Read the data and view the size of the returned variables.

```
[Z,refvec] = tbase(scalefactor,latlim,lonlim);
whos
```

| Name | Size | Bytes | Class |
|------|------|-------|-------|
|------|------|-------|-------|

| | | | |
|--------|---------|--------|--------------|
| Z | 180x360 | 518400 | double array |
| refvec | 1x3 | 24 | double array |

See Also

[etopo](#) | [gtopo30](#) | [usgsdem](#)

Introduced before R2006a

textm

Project text annotation on map axes

Syntax

```
textm(lat,lon,string)
textm(lat,lon,z,string)
textm(lat,lon,z,string,PropertyName,PropertyValue,...)
h = textm(...)
```

Description

`textm(lat,lon,string)` projects the text in `string` onto the current map axes at the locations specified by the `lat` and `lon`. The units of `lat` and `lon` must match the `'angleunits'` property of the map axes. If `lat` and `lon` contain multiple elements, `textm` places a text object at each location. In this case `string` may be a cell array of character vectors with the same number of elements as `lat` and `lon`. (For backward compatibility, `string` may also be a 2-D character array such that `size(string,1)` matches `numel(lat)`).

`textm(lat,lon,z,string)` draws the text at the altitude(s) specified in `z`, which must be the same size as `lat` and `lon`. The default altitude is 0.


`textm(lat,lon,z,string,PropertyName,PropertyValue,...)` sets the text object properties. All properties supported by the MATLAB `text` function are supported by `textm`.

`h = textm(...)` returns the handles to the text objects drawn.


Examples

The feature of `textm` that distinguishes it from the standard MATLAB `text` function is that the text object is projected appropriately. Type the following:

```
axesm sinusoid  
framem('EdgeColor','red')  
textm(60,90,'hello')
```



```
figure; axesm miller  
framem('EdgeColor','red')  
textm(60,90,'hello')
```



The text 'hello' is placed at the same geographic point, but it appears to have moved relative to the axes because of the different projections. If you change the projection using the `setm` function, the text moves as necessary. Use `text` to fix text objects in the axes independent of projection.

Tips

You may be working with scalar `lat` and `lon` data or vector `lat` and `lon` data. If you are in scalar mode and you enter a cell array of character vectors, you will get a text object containing multiple lines. Also note that vertical slash characters, rather than producing multiple lines of text, yield a single line of text containing vertical slashes. On the other hand, if `lat` and `lon` are nonscalar, then the size of the cell array input must match their size exactly.

See Also

`axesm` | `text`

Introduced before R2006a

tgrline

Read TIGER/Line data

Note `tgrline` will be removed in a future version. More recent TIGER/Line data sets are available in shapefile format and can be imported using `shaperead`.

Syntax

```
[CL,PR,SR,RR,H,AL,PL] = tgrline(filename)
[CL,PR,SR,RR,H,AL,PL] = tgrline(filename,year)
[CL,PR,SR,RR,H,AL,PL] = tgrline(filename,year,countyname)
```

Description

`[CL,PR,SR,RR,H,AL,PL] = tgrline(filename)` reads a set of 1994 TIGER/Line files which share the same filename, but different extensions. The results are returned in a set of Mapping Toolbox display structures tagged with feature names and containing:

- county boundaries (CL)
- primary roads (PR)
- secondary roads (SR)
- railroads (RR)
- hydrography (H)
- area landmarks (AL)
- point landmarks (PL)

`[CL,PR,SR,RR,H,AL,PL] = tgrline(filename,year)` reads the TIGER line files in the format from that year. The layout of TIGER/Line files is updated periodically and filename extensions may change from year to year. Valid years are 1990, 1992, 1994, 1995, 1999, 2000, 2002, 2003, and 2004.

[CL,PR,SR,RR,H,AL,PL] = tgrline(*filename*,*year*,*countyname*) uses the character vector *countyname* to tag the county data.

Background

The United States Census Bureau distributes TIGER/Line data over the Internet and via CD-ROM or DVD.

TIGER/Line files contain vector map data used to support mapping for the U.S. Census Bureau. TIGER is an acronym for Topographically Integrated Geographic Encoding and Referencing. These files contain data for political boundaries, including states, counties, Indian reservations, and census tracts, as well as roads, railroads, hydrography, and landmarks. In addition to the geographically referenced information, the files also contain data to determine the address of an object. The data covers the United States of America and its territories or administrative units: Puerto Rico, the Virgin Islands of the United States, American Samoa, Guam, the Commonwealth of the Northern Mariana Islands, the Republic of Palau, the other Pacific entities that were part of the Trust Territory of the Pacific Islands (the Republic of the Marshall Islands and the Federated States of Micronesia), and the Midway Islands. The most common application of this data is to commercial CD-ROM road atlases.

TIGER/Line is a registered trademark of the United States Census Bureau.

Examples

Read from the data for Washington, D.C.:

```
[CL,PR,SR,RR,H,AL,PL] = tgrline('TGR11001',1994,'Wash,DC');
```

Tips

This function reads only a subset of the data in the TIGER/Line files. For example, the function does not return local roads, zip codes, or census tract numbers.

Data are returned as Mapping Toolbox display structures, which you can then update to geographic data structures. For information about display structure format, see “Version 1 Display Structures” on page 1-257 in the reference page for `display`. The `updategeostruc` function performs such conversions.

See Also

shaperead | updategeostruct

Introduced before R2006a

tightmap

Remove white space around map

Syntax

```
tightmap
```

Description


`tightmap` sets the axis limits to be tight around the map in the current axes. This eliminates or reduces the white border between the map frame and the axes box. Use `axis auto` to undo `tightmap`.

Examples

Display Map of Africa With and Without Surrounding White Space


Display a map of Africa. Notice the white space between the map frame and the edge of the axes box.

```
axesm('miller','maplatlim',[-40 40],'maplonlim',[-20 60])  
framem;  
gridm;  
mlabel;  
plabel  
load coastlines  
plotm(coastlat,coastlon)
```



Now remove white space around map axes.

tightmap



Tips

The axis limits are fixed. If a change in the projection parameters changes the size or position of the map display within the projected coordinate system, execute `tightmap` again. Also note that `tightmap` needs to be re-applied following any call to `setm` that causes projected map objects to be re-projected.

The `tightmap` function performs no action on a 'globe' map axes.

See Also

`axesscale` | `panzoom` | `paperscale` | `previewmap` | `zoom`

Introduced before R2006a

timezone

Time zone based on longitude

Syntax

```
[zd,zltr,zone] = timezone(long)
[zd,zltr,zone] = timezone(long,units)
```

Description

[zd,zltr,zone] = `timezone(long)` returns an integer zone description, `zd`, an alphabetical zone indicator, `zltr`, and a character vector, `zone`, with the complete zone description and alphabetical zone indicator corresponding to the input longitude `long`.

[zd,zltr,zone] = `timezone(long,units)` specifies the angular units with a standard angle units. The default value is 'degrees'. Valid units are:

- 'degrees' — decimal degrees
- 'radians'

Examples

Given that it is locally 1330 (1:30 p.m.) at a longitude of 75°W, determine GMT:


```
[zd,zltr,zone] = timezone(-75,'degrees')
```

```
zd =
     5
zltr =
'R'
zone =
'+5 R'
```

Greenwich Mean Time (GMT) is 1330 plus five hours, or 1830 (6:30 p.m.).

Background

Time is determined by the position of the Sun relative to the prime meridian, the zero longitude line running through Greenwich, England. When this meridian lies directly below the Sun, it is noon GMT. For local times elsewhere, the Earth is divided into 15^o longitude bands, each centered on a central meridian. When a central meridian lies directly below the Sun, Local Mean Time (LMT) in that zone is noon. The zone description is an integer that when added to LMT gives GMT. For notational convenience, each zone is also given an alphabetical indicator. The indicator at Greenwich is Z, so GMT is often called *ZULU time*.



Note that there are actually 25 time zones, because the zone centered on the International Date Line (180^o E/W) is split into two: “+12 Y” and “-12 M.”

Limitations

National and local governments set their own time zone boundaries for political or geographic convenience. The `timezone` function does not account for statutory deviations from the meridian-based system.

Introduced before R2006a

tissot

Project Tissot indicatrices on map axes

Syntax

```
h = tissot
h = tissot(spec)
h = tissot(spec, linestyle)
h = tissot(linestyle)
h = tissot(spec,PropertyName,PropertyValue,...)
h = tissot(linestyle,PropertyName,PropertyValue,...)
```

Description

`h = tissot` plots the default Tissot diagram, as described above, on the current map axes and returns handles for the displayed indicatrices.

`h = tissot(spec)` allows you to specify plotting parameters of the displayed Tissot diagram as described above.

`h = tissot(spec,linestyle)` and `h = tissot(linestyle)` where *linestyle* defines the style of the Tissot indicatrices, specified as a *linespec*.

`h = tissot(spec,PropertyName,PropertyValue,...)` and `h = tissot(linestyle,PropertyName,PropertyValue,...)` allow the specification of any property and value recognized by the `line` function.

Background

Tissot indicatrices are plotting symbols that are useful for understanding the various distortions of a given map projection. The indicatrices are circles of identical true radius on the Earth's surface. When plotted on a map projection, they indicate whether the projection has certain features. If the plotted indicatrices all enclose the same area, the projection is equal area (for example, a Sinusoidal projection would have this feature). If

they all remain circular, then conformality is indicated (a Mercator projection has this property). Distortions in meridional or parallel distance are exhibited by flattened or stretched indicatrices. Many projections will show very even, circular indicatrices in some regions, often near the center, and wildly distorted indicatrices in others, such as near the edges. The Tissot diagram is therefore very useful in analyzing the appropriateness of a projection to a given purpose or region.

The general layout of the Tissot diagram is defined by the specification vector `spec`.

```
spec = [Radius]
spec = [Latint,Longint]
spec = [Latint,Longint,Radius]
spec = [Latint,Longint,Radius,Points]
```

`Radius` is the small circle radius of each indicatrix circle. If entered, it should be in the same units as the map axes `Geoid`. The default radius is 1/10th the radius of the sphere.


`Latint` is the latitude interval between indicatrix circle centers. If entered it should be in the map axes `AngleUnits`. The default value is one circle every 30° of latitude (that is, 0°, +/-30°, etc.).

`Longint` is the longitude interval between indicatrix circle centers. If entered it should be in the map axes `AngleUnits`. The default value is one circle every 30° of longitude (that is, 0°, +/-30°, etc.).

`Points` is the number of plotting points per circle. The default is 100 points.


Examples

```
axesm sinusoid; framem
tissot
```



The Sinusoidal projection is equal area.

```
setm(gca, 'MapProjection', 'Mercator')
```



The Mercator projection is conformal.

See Also

`distortcalc` | `mdistort`

Introduced before R2006a

toDegrees

Convert angles to degrees

Syntax

```
[angle1InDegrees, angle2InDegrees, ...] =  
toDegrees(fromUnits,angle1, angle2, ...)
```

Description

[angle1InDegrees, angle2InDegrees, ...] = toDegrees(fromUnits,angle1, angle2, ...) converts angle1, angle2, ... to degrees from the angle units specified in fromUnits. The value of fromUnits can be either 'degrees' or 'radians' and may be abbreviated. The inputs angle1, angle2, ... and their corresponding outputs are numeric arrays of various sizes, with size(angleNinDegrees) matching size(angleN).

See Also

fromDegrees, fromRadians, rad2deg, toRadians

Introduced in R2007b

toRadians

Convert angles to radians

Syntax

```
[angle1InRadians, angle2InRadians, ...] = toRadians(fromUnits,  
angle1, angle2, ...)
```

Description

[angle1InRadians, angle2InRadians, ...] = toRadians(*fromUnits*, angle1, angle2, ...) converts angle1, angle2, ... to radians from the angle units specified by *fromUnits*. The value of *fromUnits* can be either 'degrees' or 'radians' and may be abbreviated. The inputs angle1, angle2, ... and their corresponding outputs are numeric arrays of various sizes, with size(angleNinRadians) matching size(angleN).

See Also

deg2rad, fromDegrees, fromRadians, toDegrees

Introduced in R2007b

track

Track segments to connect navigational waypoints

Syntax

```
[latrkr,lonrkr] = track(waypts)
[latrkr,lonrkr] = track(waypts,units)
[latrkr,lonrkr] = track(lat,lon)
[latrkr,lonrkr] = track(lat,lon,ellipsoid)
[latrkr,lonrkr] = track(lat,lon,ellipsoid,units,npts)
[latrkr,lonrkr] = track(method,lat,...)
trkpts = track(lat,lon...)
```

Description

[*latrkr*,*lonrkr*] = `track(waypts)` returns points in *latrkr* and *lonrkr* along a track between the waypoints provided in navigational track format in the two-column matrix *waypts*. The outputs are column vectors in which successive segments are delineated with NaNs.

[*latrkr*,*lonrkr*] = `track(waypts,units)` specifies the units of the inputs and outputs, where *units* is any valid angle unit string. The default is 'degrees'.

[*latrkr*,*lonrkr*] = `track(lat,lon)` allows the user to input the waypoints in two vectors, *lat* and *lon*.

[*latrkr*,*lonrkr*] = `track(lat,lon,ellipsoid)` specifies the shape of the Earth using *ellipsoid*, which can be a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form [*semimajor_axis* *eccentricity*]. The default ellipsoid is a unit sphere

[*latrkr*,*lonrkr*] = `track(lat,lon,ellipsoid,units,npts)` establishes how many intermediate points are to be calculated for every track segment. By default, *npts* is 30.

[*latrkr*,*lonrkr*] = `track(method,lat,...)` establishes the logic to be used to determine the intermediate points along the track between waypoints. Because this is a

navigationally motivated function, the default method is 'rh', which results in rhumb line logic. Great circle logic can be specified with 'gc'.

`trkpts = track(lat, lon...)` compresses the output into one two-column matrix, `trkpts`, in which the first column represents latitudes and the second column, longitudes.


Examples

Calculate Track and Display It on Map

The `track` function is useful for generating data in order to display tracks. Lieutenant Sextant is the navigator of the USS Neversail. He is charged with plotting a track to take Neversail from the Straits of Gibraltar to Port Said, Egypt, the northern end of the Suez Canal. He has picked appropriate waypoints and now would like to display the track for his captain's approval.

First, display a chart of the Mediterranean Sea.

```
load coastlines
axesm('mercator', 'MapLatLimit', [28 47], 'MapLonLimit', [-10 37], ...
      'Grid', 'on', 'Frame', 'on', 'MeridianLabel', 'on', 'ParallelLabel', 'on')
geoshow(coastlat, coastlon, 'DisplayType', 'line', 'color', 'b')
```




These are the waypoints Lt. Sextant has selected.

```
waypoints = [36,-5; 36,-2; 38,5; 38,11; 35,13; 33,30; 31.5,32];
```

Now display the track. With a display this clear, the captain gladly approves the plan.

```
[lstrk,lstrk] = track('rh',waypoints,'degrees');  
geoshow(lstrk,lstrk,'DisplayType','line','color','r')
```



See Also

[dreckon](#) | [gwaypts](#) | [legs](#) | [navfix](#)

Introduced before R2006a

track1

Geographic tracks from starting point, azimuth, and range

Syntax

```
[lat,lon] = track1(lat0,lon0,az)
[lat,lon] = track1(lat0,lon0,az,arclen)
[lat,lon] = track1(lat0,lon0,az,arclen,ellipsoid)
[lat,lon] = track1(lat0,lon0,az,angleunits)
[lat,lon] = track1(lat0,lon0,az,arclen,angleunits)
[lat,lon] = track1(lat0,lon0,az,arclen,ellipsoid,angleunits)
[lat,lon] = track1(lat0,lon0,az,arclen,ellipsoid,angleunits,npts)
[lat,lon] = track1(trackstr,...)
mat = track1(...)
```

Description

`[lat,lon] = track1(lat0,lon0,az)` computes complete great circle tracks on a sphere starting at the point `lat0,lon0` and proceeding along the input azimuth, `az`. The inputs can be scalar or column vectors.

`[lat,lon] = track1(lat0,lon0,az,arclen)` uses the input `arclen` to specify the arc length of the great circle track. `arclen` is specified in units of degrees of arc. If `arclen` is a column vector, then the track is computed from the starting point, with positive distance measured easterly. If `arclen` is a two column matrix, then the track is computed starting at the range in the first column and ending at the range in the second column. If `arclen = []`, then the complete track is computed.

`[lat,lon] = track1(lat0,lon0,az,arclen,ellipsoid)` computes the track along a geodesic arc on the ellipsoid defined by the input `ellipsoid`, which can be a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. `arclen` must be expressed in length units that match the units of the semimajor axis — unless `ellipsoid` is `[]` or the semimajor axis length is zero. In these special cases, `arclen` is assumed to be in degrees of arc and the tracks are computed on a sphere, as in the preceding syntax.


```
[lat,lon] = track1(lat0,lon0,az,angleunits),
[lat,lon] = track1(lat0,lon0,az,arclen,angleunits), and
[lat,lon] = track1(lat0,lon0,az,arclen,ellipsoid,angleunits) where
angleunits defines the units of the input and output angles as 'degrees' or
'radians'.
```

```
[lat,lon] = track1(lat0,lon0,az,arclen,ellipsoid,angleunits,npts)
uses the scalar input npts to specify the number of points per track. The default value of
npts is 100.
```

```
[lat,lon] = track1(trackstr,...) where trackstr is a string scalar or a
character vector that defines either a great circle ('gc') or rhumb line track ('rh'). If
trackstr is 'gc', then either great circle (given a sphere) or geodesic (given an
ellipsoid) tracks are computed. If trackstr is 'rh', then the rhumb line tracks are
computed.
```

```
mat = track1(...) returns a single output argument mat such that mat = [lat
lon]. This is useful if only a single track is computed.
```


Multiple tracks can be defined from a single starting point by providing scalar `lat0` and `lon0` and column vectors for `az` and `arclen`.

Examples

```
% Set up the axes.
axesm('mercator','MapLatLimit',[-60 60],'MapLonLimit',[-60 60])
gridm on; plabel on; mlabel on;
```

```
% Plot the great circle track in green.
[lattrkgc,lontrkgc] = track1(0,0,45,[-55 55]);
plotm(lattrkgc,lontrkgc,'g')
```

```
% Plot the rhumb line track in red.
[lattrkrh,lontrkrh] = track1('rh',0,0,45,[-55 55]);
plotm(lattrkrh,lontrkrh,'r')
```



Definitions

Track Lines

A path along the surface of the Earth connecting two points is a *track*. Two types of track lines are of interest geographically, *great circles* and *rhumb lines*. Great circles represent the shortest possible path between two points. Rhumb lines are paths with constant angular headings. They are not, in general, the shortest path between two points.

Full great circles bisect the Earth; the ends of the track meet to form a complete circle. Rhumb lines with true east or west azimuths are parallels; the ends also meet to form a complete circle. All other rhumb lines terminate at the poles; their ends do not meet.

See Also

[azimuth](#) | [distance](#) | [reckon](#) | [scircle1](#) | [scircle2](#) | [track](#) | [track2](#) | [trackg](#)

Introduced before R2006a

track2

Geographic tracks from starting and ending points

Syntax

```
[lat,lon] = track2(lat1,lon1,lat2,lon2)
[lat,lon] = track2(lat1,lon1,lat2,lon2,ellipsoid)
[lat,lon] = track2(lat1,lon1,lat2,lon2,units)
[lat,lon] = track2(lat1,lon1,lat2,lon2,ellipsoid,units)
[lat,lon] = track2(lat1,lon1,lat2,lon2,ellipsoid,units,npts)
[lat,lon] = track2(track,...)
mat = track2(...)
```

Description

`[lat,lon] = track2(lat1,lon1,lat2,lon2)` computes great circle tracks on a sphere starting at the point `lat1,lon1` and ending at `lat2,lon2`. The inputs can be scalar or column vectors.

`[lat,lon] = track2(lat1,lon1,lat2,lon2,ellipsoid)` computes the great circle track on the ellipsoid defined by the input `ellipsoid`. `ellipsoid` is a `referenceSphere`, `referenceEllipsoid`, or `oblateSpheroid` object, or a vector of the form `[semimajor_axis eccentricity]`. If `ellipsoid = []`, a sphere is assumed.

`[lat,lon] = track2(lat1,lon1,lat2,lon2,units)` and `[lat,lon] = track2(lat1,lon1,lat2,lon2,ellipsoid,units)` are both valid calling forms, which use the input `units` to define the angle units of the inputs and outputs. If you omit `units`, 'degrees' is assumed.


`[lat,lon] = track2(lat1,lon1,lat2,lon2,ellipsoid,units,npts)` uses the scalar input `npts` to determine the number of points per track computed. The default value of `npts` is 100.

`[lat,lon] = track2(track,...)` uses the track to define either a great circle or a rhumb line track. If `track = 'gc'`, then great circle tracks are computed. If `track = 'rh'`, then rhumb line tracks are computed. If you omit track, 'gc' is assumed.

`mat = track2(...)` returns a single output argument where `mat = [lat lon]`. This is useful if a single track is computed. Multiple tracks can be defined from a single starting point by providing scalar inputs for `lat1, lon1` and column vectors for `lat2, lon2`.

Examples

```
% Set up the axes.  
axesm('mercator','MapLatLimit',[30 50],'MapLonLimit',[-40 40])  
  
% Calculate the great circle track.  
[latrkgc,lontrkgc] = track2(40,-35,40,35);  
  
% Calculate the rhumb line track.  
[latrkrh,lontrkrh] = track2('rh',40,-35,40,35);  
  
% Plot both tracks.  
plotm(latrkgc,lontrkgc,'g')  
plotm(latrkrh,lontrkrh,'r')
```



Definitions

Track Lines

A path along the surface of the Earth connecting two points is a *track*. Two types of track lines are of interest geographically, *great circles* and *rhumb lines*. Great circles represent the shortest possible path between two points. Rhumb lines are paths with constant angular headings. They are not, in general, the shortest path between two points.

See Also

azimuth | distance | reckon | scircle1 | scircle2 | track | track1 | trackg

Introduced before R2006a

trackg

Great circle or rhumb line defined via mouse input

Syntax

```
h = trackg(ntrax)
h = trackg(ntrax,npts)
h = trackg(ntrax,linestyle)
h = trackg(ntrax,PropertyName,PropertyValue,...)
[lat,lon] = trackg(ntrax,npts,...)
h = trackg(track,ntrax,...)
```

Description

`h = trackg(ntrax)` brings forward the current map axes and waits for the user to make $(2 \times ntrax)$ mouse clicks. The output `h` is a vector of handles for the `ntrax` track segments, which are then displayed.

`h = trackg(ntrax,npts)` specifies the number of plotting points to be used for each track segment. `npts` is 100 by default.

`h = trackg(ntrax,linestyle)` specifies the line style for the displayed track segments, where `linestyle` is a `linespec` that defines the style of the line.

`h = trackg(ntrax,PropertyName,PropertyValue,...)` allows property name/property value pairs to be set, where `PropertyName` and `PropertyValue` are recognized by the `line` function.

`[lat,lon] = trackg(ntrax,npts,...)` returns the coordinates of the plotted points rather than the handles of the track segments. Successive segments are stored in separate columns of `lat` and `lon`.

`h = trackg(track,ntrax,...)` specifies the logic with which tracks are calculated. If `track` is 'gc' (the default), a great circle path is used. If `track` is 'rh', rhumb line logic is used.

This function is used to define great circles or rhumb lines for display using mouse clicks. For each track, two clicks are required, one for each endpoint of the desired track segment. You can modify the track after creation by **Shift**+clicking it. The track is then in edit mode, during which you can change the length and position by dragging control points, or by entering values into a control panel. **Shift**+clicking again exits edit mode.

See Also

`scircleg` | `track1` | `track2`

Introduced before R2006a

trimcart

Trim graphic objects to map frame

Syntax

```
trimcart(h)
```

Description


`trimcart(h)` clips the graphic objects to the map frame. `h` can be a handle or a vector of handles to graphics objects. `h` can also be any object name recognized by `handlem`. `trimcart` clips lines, surfaces, and text objects.

Examples

Trim Graphic Objects to Map Frame

Trim graphic objects to map frame.

```
figure;  
axesm('miller')  
framem  
[x, y] = humps(0:.05:1);  
h = plot(x, y/25, 'r+-');  
load coastlines  
geoshow(coastlat, coastlon)  
trimcart(h)
```



Limitations

`trimcart` does not trim patch objects.

See Also

`handlem` | `makemapped`

Introduced before R2006a

trimdata

Trim map data exceeding projection limits

Syntax

```
[ymat,xmat,trimpts] = trimdata(ymat,ylim,xmat,xlim,object)
```

Description

`[ymat,xmat,trimpts] = trimdata(ymat,ylim,xmat,xlim,object)` identifies points in map data that exceed projection limits. The projection limits are defined by the lower and upper inputs. The particular object to be trimmed is identified by the `object` input.

Allowable objects are

- 'surface' for trimming graticules
- 'light' for trimming lights,
- 'line' for trimming lines
- 'patch' for trimming patches
- 'text' for trimming text object location points
- 'none' to skip all trimming operations

See Also

`clipdata` | `undoclip` | `undotrim`

Introduced before R2006a

undoclip

Remove object clips introduced by `clipdata`

Syntax

```
[lat,long] = undoclip(lat,long,clippts,'object')
```

Description

`[lat,long] = undoclip(lat,long,clippts,'object')` removes the object clips introduced by `clipdata`. This function is necessary to properly invert projected data from the Cartesian space to the original latitude and longitude data points.

The input variable, `clippts`, must be constructed by the function `clipdata`.

Allowable objects are

- 'surface' for trimming graticules
- 'light' for trimming lights
- 'line' for trimming lines
- 'patch' for trimming patches
- 'text' for trimming text object location points
- 'none' to skip all trimming operations

See Also

`clipdata` | `trimdata` | `undotrim`

Introduced before R2006a

undotrim

Remove object trims introduced by `trimdata`

Syntax

```
[ymat,xmat] = undotrim(ymat,xmat,trimpts,object)
```

Description

`[ymat,xmat] = undotrim(ymat,xmat,trimpts,object)` removes the object trims introduced by `trimdata`. This function is necessary to properly invert projected data from the Cartesian space to the original latitude and longitude data points.

The input variable, `trimpts`, must be constructed by the function `trimdata`.

Allowable objects are

- 'surface' for trimming graticules
- 'light' for trimming lights
- 'line' for trimming lines
- 'patch' for trimming patches
- 'text' for trimming text object location points
- 'none' to skip all trimming operations

See Also

`clipdata` | `trimdata` | `undoclip`

Introduced before R2006a

unitsratio

Unit conversion factors

Syntax

```
ratio = unitsratio(to,from)
```

Description

`ratio = unitsratio(to,from)` returns the number of `to` units per one `from` unit. You can specify any of the measurement units supported by the `validateLengthUnit` function, such as kilometers, or the angle units 'radians' and 'degrees'.

For example, using measurement units, `unitsratio('cm','m')` returns the value 100 because there are 100 centimeters per meter.

The variables `to` and `from` are case insensitive and can be either singular or plural. For example, `unitsratio` accepts any of the values listed in the following table for angle units.

| Unit Name | Acceptable Values |
|-----------|--------------------|
| radian | 'rad', 'radian(s)' |
| degree | 'deg', 'degree(s)' |

The `unitsratio` function makes it easy to convert values from one system of units to another. For example, if you want to convert the value 100 kilometers (`from` units) to meters (`to` units), you can use the following code:

```
y = unitsratio('meters','kilometers') * 100
```

```
y =
```

```
100000
```

Examples

```
% Approximate mean earth radius in meters
radiusInMeters = 6371000

% Conversion factor
feetPerMeter = unitsratio('feet', 'meter')

% Radius in (international) feet:
radiusInFeet = feetPerMeter * radiusInMeters

% The following prints a true statement for valid TO, FROM pairs:
to = 'feet';
from = 'mile';
sprintf('There are %g %s per %s.', unitsratio(to,from), to, from)

% The following prints a true statement for valid TO, FROM pairs:
to = 'degrees';
from = 'radian';
sprintf('One %s is %g %s.', from, unitsratio(to,from), to)
```

See Also

[imdilate](#) | [validateLengthUnit](#)

unitstr

Check spatiotemporal unit names and abbreviations

Note The `unitstr` function is obsolete and will be removed in a future release. The syntax `str = unitstr(str, 'times')` has already been removed.

Syntax

```
unitstr
str = unitstr(str0, 'angles')
str = unitstr(str0, 'distances')
```

Description

`unitstr`, with no arguments, displays a list of names and abbreviations, recognized by certain Mapping Toolbox functions, for units of angle and length/distance.

`str = unitstr(str0, 'angles')` checks for valid angle unit names or abbreviations. If a valid name or abbreviation is found, it is converted to a standardized, preset name. 'angles' can be abbreviated.

`str = unitstr(str0, 'distances')` checks for valid length unit names or abbreviations. If a valid name or abbreviation is found, it is converted to a standardized, preset name. 'distances' can be abbreviated. Note that 'miles' and 'mi' are converted to 'statutemiles'; there is no way to specify international miles in the `unitstr` function.

Examples

This function recognizes and standardizes certain abbreviations:

```
str = unitstr('sm', 'distances')
```



```
str =  
statutemiles
```

And any unique truncation:

```
str = unitstr('ra', 'angles')
```

```
str =  
radians
```

See Also

unitsratio

Introduced before R2006a

unwrapMultipart

Unwrap vector of angles with NaN-delimited parts

Syntax

```
unwrapped = unwrapMultipart(p)
unwrapped = unwrapMultipart(p,angleUnit)
```

Description

`unwrapped = unwrapMultipart(p)` unwraps a row or column vector of azimuths, longitudes, or phase angles. Input and output units are both radians. If `p` is separated into multiple parts delimited by values of NaN, each part is unwrapped independently. If `p` has only one part, the result is equivalent to `unwrap(p)`. The output is the same size as the input and has NaNs in the same locations.

`unwrapped = unwrapMultipart(p,angleUnit)` unwraps a row or column vector of azimuths, longitudes, or phase angles, where `angleUnit` specifies the unit used for the input and output angles: 'degrees' or 'radians'.

Examples

Example 1

Compare the behavior `unwrapMultipart` to that of `unwrap`. The output of `unwrapMultipart` starts over again at 6.11 following the NaN, unlike the output of `unwrap`. The output of `unwrapMultipart` is equivalent to a concatenation (with NaN-separator) of separate calls to `unwrap`:

```
p1 = [0.17      5.67      4.89      4.10];
p2 = [6.11     1.05     2.27];
unwrap([p1 NaN p2])

ans =
    0.1700    -0.6132    -1.3932    -2.1832         NaN    -0.1732    1.0500    2.2700
```

```

unwrapMultipart([p1 NaN p2])
ans =
    0.1700   -0.6132   -1.3932   -2.1832     NaN     6.1100     7.3332     8.5532
[unwrap(p1) NaN unwrap(p2)]
ans =
    0.1700   -0.6132   -1.3932   -2.1832     NaN     6.1100     7.3332     8.5532

```


Example 2

Wrap two revolutions of a sphere to π with `wrapToPi`, and then unwrap it with `unWrapMultipart`:

```

lon = wrapToPi(deg2rad(0:10:720));
unwrappedlon = unwrapMultipart(lon);
figure; hold on
plot(lon,'--')
plot(unwrappedlon)
xlabel 'Point Number'
ylabel 'Longitude in radians'

```



See Also

[unwrap](#) | [wrapTo180](#) | [wrapTo2Pi](#) | [wrapTo360](#) | [wrapToPi](#)

Introduced in R2007b

updategeostruct

Convert line or patch display structure to geostruct

Syntax

```
geostruct = updategeostruct(displaystruct)
geostruct = updategeostruct(displaystruct, str)
[geostruct,symbolspec] = updategeostruct(displaystruct, ...)
[geostruct,symbolspec] = updategeostruct(displaystruct, ..., cmap)
```

Description

`geostruct = updategeostruct(displaystruct)` accepts a Mapping Toolbox display structure `displaystruct`. If `displaystruct` is a vector display structure for which the 'type' field has value 'line' or 'patch', `updategeostruct` restructures its elements to create a `geostruct`, `geostruct`. If `displaystruct` is a already geographic data structure, it is copied unaltered to `geostruct`. `updategeostruct` does not update display structure arrays of type 'text', 'light', 'regular', or 'surface'.

`geostruct = updategeostruct(displaystruct, str)` selects only elements whose `tag` field begins with the string scalar or character vector `str` (and whose type field is either 'line' or 'patch'). The selection is case insensitive.


`[geostruct,symbolspec] = updategeostruct(displaystruct, ...)` restructures a display structure and determines a `symbolspec` based on the graphic properties specified in the `otherproperty` field for each element of `displaystruct` and, if necessary, the `jet` colormap.

`[geostruct,symbolspec] = updategeostruct(displaystruct, ..., cmap)` specifies a colormap, `cmap`, to define the colors used in `symbolspec`.

Examples

Update and display the Great Lakes display structure to a `geostruct`:

```
load greatlakes
cmap = cool(3*numel(greatlakes));
[gtlakes, spec] = updategeostruct(greatlakes, cmap);
lat = extractfield(gtlakes, 'Lat');
lon = extractfield(gtlakes, 'Lon');
lonlim = [min(lon) max(lon)];
latlim = [min(lat) max(lat)];
figure
usamap(latlim, lonlim);
geoshow(gtlakes, 'SymbolSpec', spec)
```



Tips

There are two Mapping Toolbox encodings for vector features that use MATLAB structure arrays. In both cases there is one feature per array element, and in both cases a given array's elements all held the same type of feature. Version 1.3.1 and earlier of the Mapping Toolbox software only supported Mapping Toolbox display structures. Version 2.0 introduced a data structure for vector geodata which was less rigidly defined and more open-ended. The new structures are called *geostructs* (if they contain geographic coordinate data) and *mapstructs* (if they contain projected coordinate data). Over time,

display structures are being phased out of the toolbox; the `updategeostruct` function is provided to help users migrate from the old display structure format to the current `geostruct/mapstruct` format.

A Version 1 Mapping Toolbox display structure is a MATLAB structure that can contain line, patch, text, regular data grid, geolocated data grid, and light objects. The `displaym` function does not accept geostructs produced by Version 2 of the Mapping Toolbox software.

Display structures for lines and patches and Line and Polygon geostructs have the following things in common:

- A field that specifies the type of feature geometry:
 - A `type` field a display structure (value: 'line' or 'patch')
 - A `Geometry` field for a geostruct (value: 'Line' or 'Polygon')
- A latitude field:
 - `lat` for a display structure
 - `Lat` for a geostruct
- A longitude field:
 - `long` for a display structure
 - `Lon` for a geostruct

In terms of their differences,

- A geostruct has a `BoundingBox` field; there is no display structure counterpart for this
- A geostruct typically has one or more “attribute” fields, whose values must be either scalar doubles or character vectors, with arbitrary field names. The presence or absence of a given attribute field—and its value—is dependent on the specific data set that the geostruct represents.
- A (line or patch) display structure has the following fields:
 - A `tag` field that names an individual feature or object
 - An `altitude` coordinate array that extends coordinates to 3-D
 - An `otherproperty` field in which MATLAB graphics can be specified explicitly, on a per-feature basis

Object properties used in the display are taken from the `otherproperty` field of the structure. If a line or patch object's `otherproperty` field is empty, `displaym` uses default colors. A patch is assigned an index into the current colormap based on the structure's `tag` field. Lines are assigned colors from the current color order according to their tags.

The newer `geostruct` representation has significant advantages:

- It can represent a much wider range of attributes (display structures essentially can represent only a feature name).
- The `geostruct` representation (in combination with `geoshow` and `makesymbolspec`) keeps graphics display properties separate from the intrinsic properties of the geographic features themselves.

For example, a road-class attribute can be used to display major highways with a distinctive color and greater line width than secondary roads. The same geographic data structure can be displayed in many different ways, without altering any of its contents, and shapefile data imported from external sources need not be altered to control its graphic display.

For information about the display structure format, see “Version 1 Display Structures” on page 1-257 in the reference page for `displaym`. For a discussion of the characteristics of geographic data structures, see “Geographic Data Structures” in the *Mapping Toolbox User's Guide*.

See Also

`displaym` | `geoshow` | `makesymbolspec` | `mapshow` | `mapview` | `shaperead`

Introduced before R2006a

updateLayers

Update layer properties

Syntax

```
[updatedLayer, index] = updateLayers(server, layer)
```

Description

[updatedLayer, index] = updateLayers(server, layer) returns an array of WMSLayer objects and updates the layer properties with values from the Web map server, server. The WMSLayer array layer must contain only one unique ServerURL. The updateLayers function removes layers no longer available on the server. The logical array index contains true for each available layer.

Examples

Update Properties of MODIS Global Mosaic Layer

Update the properties of a MODIS global mosaic layer obtained from the NASA Earth Observations WMS server.

```
nasa = wmsfind('NASA Earth Observations', 'SearchField', 'any');  
modis = refine(nasa, 'land*day*month');  
modis = modis(1);
```

Create a WebMapServer object.


```
server = WebMapServer(modis.ServerURL);
```

Update the properties of the MODIS layer.

```
updatedLayer = updateLayers(server, modis);
```

Obtain the map and display it.

```
mapRequest = WMSMapRequest(updatedLayer, server);  
A = getMap(server, mapRequest.RequestURL);  
R = mapRequest.RasterReference;  
figure  
ax = worldmap('world');  
geoshow(A,R)  
setm(ax, 'MLabelParallel', -90, 'MLabelLocation', 90)  
title({'MODIS Global Mosaic', modis.LayerTitle})
```



View the metadata of the layer.

```
metadata = webread(updatedLayer.Details.MetadataURL);  
disp(metadata)
```

Update Properties of Layers from Multiple Servers

Find layers from USGS servers with the word “image” in the server URL.

```
usgsLayers = wmsfind('usgs*image','SearchField','serverurl');
```

Find the layers for an individual server, update their properties, and append them to the updatedLayers array.

```
serverURLs = usgsLayers.servers;
updatedLayers = [];
fprintf('Updating layer properties from %d servers.\n', ...
    numel(serverURLs));
for k=1:numel(serverURLs)
    serverLayers = refine(usgsLayers, serverURLs{k}, ...
        'SearchField','serverurl','MatchType','exact');
    serverURL = serverLayers(1).ServerURL;
    fprintf('Updating properties from server %d:\n%s\n', ...
        k, serverURL);
    server = WebMapServer(serverURL);
    try
        layers = updateLayers(server,serverLayers);
        % Grow using concatenation because layers can have any
        % length ranging from 0 to numel(serverLayers).
        updatedLayers = [updatedLayers; layers];
    catch e
        fprintf('Server %s is not responding.\n', ...
            serverURL);
        fprintf('Error message is %s\n', e.message)
    end
end
```

Input Arguments

server — Web map server

array of WebMapServer objects

Web map server, specified as an array of WebMapServer objects.

layer — Web map service layers

WMSLayer object

Web map service layer, specified as a WMSLayer object.

Output Arguments

updatedLayer — Updated Web map service layers

array of `WMSLayer` objects.

Updated Web map service layers, returned as an array of `WMSLayer` objects. `updatedLayers` has the same size as `layer(index)`.

index — Availability of layers

logical array

Availability of layers, returned as a logical array. `index` contains `true` for each available layer.

Tips

`updateLayers` accesses the Internet to update the properties. Occasionally, a WMS server is unavailable, or several minutes elapse before the properties are updated.

See Also

Introduced before R2006a

usamap

Construct map axes for United States of America

Syntax

```
usamap state
usamap(state)
usamap 'conus'
usamap('conus')
usamap
usamap(latlim,lonlim)
usamap(Z,R)
h = usamap(____)
h = usamap('all')
```

Description

`usamap state` and

`usamap(state)` create an empty map axes with a Lambert Conformal Conic projection and map limits covering a U.S. state or group of states specified by `state`. The map axes is created in the current axes and the axis limits are set tight around the map frame.

`usamap 'conus'` and

`usamap('conus')` create an empty map axes for the conterminous 48 states (that is, all states excluding Alaska and Hawaii).

`usamap` with no arguments presents a menu from which you can select a single state, the District of Columbia, the conterminous 48 states, or all states.

`usamap(latlim,lonlim)` creates an empty Lambert Conformal map axes for a region of the U.S. defined by its latitude and longitude limits in degrees.

`usamap(Z,R)` derives the map limits from the extent of a regular data grid, `Z`, georeferenced by `R`.

`h = usamap(___)` returns the handle of the map axes.

`h = usamap('all')` constructs three empty map axes, inset within a single figure, for the conterminous states, Alaska, and Hawaii, with a spherical Earth model and other projection parameters suggested by the U.S. Geological Survey. The maps in the three axes are shown at approximately the same scale. The handles for the three map axes are returned in `h`.

`usamap('allequal')` is the same as `usamap('all')`, but usage of `'allequal'` will be removed in a future release.

Examples


Make a Map of Alabama

Make a map of the state of Alabama only.

```
figure
usamap('Alabama')
alabamahi = shaperead('usastatehi', 'UseGeoCoords', true, ...
    'Selector', {@(name) strcmpi(name, 'Alabama'), 'Name'});
geoshow(alabamahi, 'FaceColor', [0.3 1.0, 0.675])
```

Add text to label the state.

```
textm(alabamahi.LabelLat, alabamahi.LabelLon, alabamahi.Name, ...
    'HorizontalAlignment', 'center')
```




Map a Region Extending From California to Montana

Make a map of a contiguous landmass that contains California and Montana.

```
figure
ax = usamap({'CA', 'MT'});
set(ax, 'Visible', 'off')
latlim = getm(ax, 'MapLatLimit');
lonlim = getm(ax, 'MapLonLimit');
states = shaperead('usastatehi',...
    'UseGeoCoords', true, 'BoundingBox', [lonlim', latlim']);
geoshow(ax, states, 'FaceColor', [0.5 0.5 1])
```

Add labels to each state.

```
lat = [states.LabelLat];  
lon = [states.LabelLon];  
tf = ingeoquad(lat, lon, latlim, lonlim);  
textm(lat(tf), lon(tf), {states(tf).Name}, ...  
      'HorizontalAlignment', 'center')
```




Map the Conterminous United States

Map the conterminous United States with a different fill color for each state.


```
figure
ax = usamap('conus');
states = shaperead('usastatelo', 'UseGeoCoords', true,...
    'Selector',...
    {@(name) ~any(strcmp(name,{'Alaska','Hawaii'})), 'Name'});
faceColors = makesymbolspec('Polygon',...
    {'INDEX', [1 numel(states)], 'FaceColor', ...
    polcmap(numel(states))}); %NOTE - colors are random
geoshow(ax, states, 'DisplayType', 'polygon', ...
    'SymbolSpec', faceColors)
```

Set optional display settings.

```
framem off; gridm off; mlabel off; plabel off;
```



Map the USA Including Alaska and Hawaii

Map the USA with separate axes for Alaska and Hawaii.


```
figure
ax = usamap('all');
set(ax, 'Visible', 'off')
states = shaperead('usastatelo', 'UseGeoCoords', true);
names = {states.Name};
indexHawaii = strcmp('Hawaii', names);
indexAlaska = strcmp('Alaska', names);
indexConus = 1:numel(states);
indexConus(indexHawaii|indexAlaska) = [];
stateColor = [0.5 1 0.5];
```

Display the three regions.

```
geoshow(ax(1), states(indexConus), 'FaceColor', stateColor)
geoshow(ax(2), states(indexAlaska), 'FaceColor', stateColor)
geoshow(ax(3), states(indexHawaii), 'FaceColor', stateColor)
```

Hide the frame.

```
for k = 1:3
    setm(ax(k), 'Frame', 'off', 'Grid', 'off', ...
        'ParallelLabel', 'off', 'MeridianLabel', 'off')
end
```



Input Arguments

state — State to display

character vector | string scalar | string array | cell array of character vectors |
'District of Columbia' | 'Alabama' | 'AL' | 'Alaska' | 'AK' | ...

State to display, specified as a string scalar, string array, character vector or cell array of character vectors. Permissible values include names of states, standard two-letter U.S. Postal Service abbreviations for states, and 'District of Columbia'.

Example: `usamap({'Maine', 'Florida'})` sets the map limits to cover the region spanning from Maine to Florida.

latlim — Latitude limits

two-element vector

Latitude limits, specified as a two-element vector of the form `[southern_limit northern_limit]`.

lonlim — Longitude limits

two-element vector

Longitude limits, specified as a two-element vector of the form `[western_limit eastern_limit]`.

Z — Data grid

M-by-*N* array

Data grid, specified as an *M*-by-*N* array. *Z* is a regular data grid associated with a geographic reference *R*.

R — Geographic reference

geographic raster reference object | vector | matrix

Geographic reference, specified as one of the following.

| Type | Description |
|------------------------------------|---|
| Geographic raster reference object | GeographicCellsReference or GeographicPostingsReference geographic raster reference object. The RasterSize property must be consistent with the size of the data grid, <code>size(Z)</code> . |
| Vector | 1-by-3 numeric vector with elements: <code>[cells/degree northern_latitude_limit western_longitude_limit]</code> |

| Type | Description |
|--------|--|
| Matrix | <p>3-by-2 numeric matrix that transforms raster row and column indices to or from geographic coordinates according to:</p> $[\text{lon } \text{lat}] = [\text{row } \text{col } 1] * R$ <p>R defines a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel.</p> |

For more information about referencing vectors and matrices, see “Georeferenced Raster Data”.

Output Arguments

h — Handle of the map axes

handle object | array of handle objects

Handle of the map axes, returned as a handle object.

If you use the syntax `h = usamap('all')`, then `h` is array of handle objects. `h(1)` is for the conterminous states, `h(2)` is for Alaska, and `h(3)` is for Hawaii.

Tips

- All axes created with `usamap` are initialized with a spherical Earth model having a radius of 6,371,000 meters.
- In some cases, `usamap` uses `tightmap` to adjust the axis limits tight around the map. If you change the projection, or just want more white space around the map frame, use `tightmap` again or `axis auto`.
- `axes(h(n))`, where `n = 1, 2, or 3`, makes the desired axes current.
- `set(h, 'Visible', 'on')` makes the axes visible.
- `axesscale(h(1))` resizes the axes containing Alaska and Hawaii to the same scale as the conterminous states.

See Also

`axesm` | `axesscale` | `geoshow` | `paperscale` | `plotedit` | `tightmap` | `worldmap`

Introduced before R2006a

usgs24kdem

Read USGS 7.5 minute (30 meter or 10 meter) Digital Elevation Models

Syntax

```
[lat,lon,Z] = usgs24kdem  
[lat,lon,Z] = usgs24kdem(filename)  
[lat,lon,Z] = usgs24kdem(filename,samplefactor)  
[lat,lon,Z] = usgs24kdem(filename,samplefactor,latlim,lonlim)  
[lat,lon,Z] = usgs24kdem(filename,samplefactor,latlim,lonlim,gsize)  
[lat,lon,Z,header,profile] = usgs24kdem( ___ )
```

Description

[lat,lon,Z] = usgs24kdem reads a USGS 1:24,000 digital elevation map (DEM) file in standard format. You select the file interactively. usgs24kdem reads the entire file, subsampled by a factor of 5, returning a geolocated data grid with a latitude array, lat, longitude array, lon, and an elevation array, Z. Horizontal units are in degrees, vertical units might vary. The 1:24,000 series of DEMs store data as a grid of elevations spaced either at 10 or 30 meters apart. The number of points in a file varies with the geographic location.

[lat,lon,Z] = usgs24kdem(filename) reads the USGS DEM specified by filename and returns the result as a geolocated data grid.

[lat,lon,Z] = usgs24kdem(filename,samplefactor) reads a subset of the DEM data from filename, where samplefactor is a scalar integer that specifies the sample frequency.

[lat,lon,Z] = usgs24kdem(filename,samplefactor,latlim,lonlim) reads the subset of the elevation data from filename specified by the two-element vectors latlim and lonlim. You specify the latitude and longitude limits in degrees. Elements in the vectors must be in ascending order. The data might extend outside the requested area.

`[lat,lon,Z] = usgs24kdem(filename,samplefactor,latlim,lonlim,gsize)` specifies the graticule size in `gsize`. `gsize` is a two-element vector specifying the number of rows and columns in the latitude and longitude coordinated grid.

`[lat,lon,Z,header,profile] = usgs24kdem(____)` also returns the contents of the header and raw profiles of the DEM file. The `header` structure contains descriptions of the data from the file header. The `profile` structure is the raw profile data from which the geolocated data grid is constructed.

Examples

Read USGS 24K DEM file

This example shows how to read a USGS 24K Digital Elevation Model file.

Unzip a USGS 24K DEM file. The toolbox includes a DEM file `sanfranciscos.dem.gz`.

```
filenames = gunzip('sanfranciscos.dem.gz', tempdir);  
demFilename = filenames{1};
```

Read every other point of the 1:24,000 DEM file.

```
[lat,lon,Z,header,profile] = usgs24kdem(demFilename,2);
```

Delete the temporary gunzipped file.

```
delete(demFilename);
```

As no negative elevations exist, move all points at sea level to -1 to color them blue.

```
Z(Z==0) = -1;
```

Compute the latitude and longitude limits for the DEM.

```
latlim = [min(lat(:)) max(lat(:))]
```

```
latlim = 1x2
```

```
    37.6249    37.7504
```


```
lonlim = [min(lon(:)) max(lon(:))]
```



```
lonlim = 1x2  
-122.5008 -122.3740
```

Display the DEM values.

```
figure  
usamap(latlim, lonlim)  
geoshow(lat, lon, Z, 'DisplayType','surface')  
demcmap(Z)  
daspectm('m',1)
```



Examine the metadata in the header.

header

header = struct with fields:

```
    Quadranglename: 'SAN FRANCISCO SOUTH, CA  BIG BASIN DEM  '
    TextualInfo:    'WMC                                CTOG  '
    Filler:        ''
    ProcessCode:   ''
    Filler2:       ''
    SectionalIndicator: ''
    MCoriginCode:  ''
    DEMlevelCode:  2
    ElevationPatternCode: 'regular'
    PlanimetricReferenceSystemCode: 'UTM'
    Zone:          10
    ProjectionParameters: [0 0 0 0 0 0 0 0 0 0 0 0 0 0 0]
    HorizontalUnits: 'meters'
    ElevationUnits:  'feet'
    NsidesToBoundingBox: 4
    BoundingBox: [1x8 double]
    MinMaxElevations: [0 1314]
    RotationAngle: 0
    AccuracyCode: 'accuracy information in record C'
    XYZresolutions: [30 30 1]
    NrowsCols: [1 371]
    MaxPcontourInt: NaN
    SourceMaxCintUnits: 'unknown'
    SmallestPrimary: NaN
    SourceMinCintUnits: 'unknown'
    DataSourceDate: NaN
    DataInspRevDate: NaN
    InspRevFlag: ''
    DataValidationFlag: 'unknown'
    SuspectVoidFlag: 'unknown'
    VerticalDatum: 'unknown'
    HorizontalDatum: 'unknown'
    DataEdition: NaN
    PercentVoid: NaN
```

Input Arguments

filename — Name of file containing the digital elevation map

string scalar | character array

Name of file containing the digital elevation map, specified as a string scalar or character array.

Data Types: char | string

samplefactor — Data sampling factor

5 (default) | scalar integer

Data sampling factor, specified as a scalar integer. For example, if `samplefactor` is equal to 1, `usgs24kdem` reads the data at its full resolution, that is, every pixel. If you specify a `samplefactor` value `n` that is greater than 1, `usgs24kdem` reads every `n`th point.

Data Types: double

latlim — Limits of the desired data

two-element vector

Limits of the desired data, specified as a two-element vector, in degrees. The limits must be in ascending order. The data might extend outside the requested area.

Data Types: double

lonlim — Limits of desired data

two-element vector

Limits of desired data, specified as a two-element vector, in degrees.

Data Types: double

gsize — Graticule size

same size as geolocated data grid (default) | two-element vector

Graticule size, specified as a two-element vector. `gsize` specifies the number of rows and columns in the latitude and longitude coordinated grid. If omitted, `usgs24kdem` returns a graticule the same size as the geolocated data grid. To specify the coordinated grid size without specifying the geographic limits, use empty matrices for `latlim` and `lonlim`.

Data Types: double

Output Arguments

lat — Latitude array

matrix of class `double`

Latitude array, returned as a matrix of class `double`.

lon — Longitude array

matrix of class `double`

Longitude array, returned as a matrix of class `double`.

Z — Elevation array

matrix of class `double`

Elevation array, returned as a matrix of class `double`.

header — Descriptions of the data from the file header

`struct`

Descriptions of the data from the file header, returned as a `struct`.

profile — Raw profile data from which the geolocated data grid is constructed

`struct`

Raw profile data from which the geolocated data grid is constructed, returned as a `struct`.

Tips

- The U.S. Geological Survey has created a series of digital elevation models based on their paper 1:24,000 scale maps. The grid spacing for these elevations models is either 10 meters or 30 meters on a Universal Transverse Mercator grid. Each file covers a 7.5-minute quadrangle. The map and data series are available for much of the conterminous United States, Hawaii, and Puerto Rico. The data has been released in several formats. This function reads the data in the “standard” file format.
- This function reads USGS DEM files stored in the UTM projection. The function unprojects the grid back to latitude and longitude. Use `usgsdem` for data stored in geographic grids.

- The number of points in a file varies with the geographic location. Unlike the USGS DEM products, which use an equal-angle grid, the UTM projection grid DEMs cannot simply be concatenated to cover larger areas. There can be data gaps between DEMs.
- You can obtain the data files from the U.S. Geological Survey and from commercial vendors . Other agencies have made some local area data available online. See “Find Geospatial Data Online”. The DEM files are ASCII files, and can be transferred as text. Line-ending conversion is not necessarily required.

See Also

demdataui | dted | etopo | gtopo30 | tbase | usgsdem | usgsdems

Introduced before R2006a

usgsdem

Read USGS 1-degree (3-arc-second) Digital Elevation Model

Syntax

```
[Z,refvec] = usgsdem(filename,scalefactor)
[Z,refvec] = usgsdem(filename,scalefactor,latlim,lonlim)
```

Description

`[Z,refvec] = usgsdem(filename,scalefactor)` reads the specified file and returns the data in a regular data grid along with referencing vector `refvec`, a 1-by-3 vector having elements `[cells/degree north-latitude west-longitude]` with latitude and longitude limits specified in degrees. The data can be read at full resolution (`scalefactor = 1`), or can be downsampled by the `scalefactor`. A `scalefactor` of 3 returns every third point, giving 1/3 of the full resolution.

`[Z,refvec] = usgsdem(filename,scalefactor,latlim,lonlim)` reads data within the latitude and longitude limits. These limits are two-element vectors with the minimum and maximum values specified in units of degrees.

Background

The U.S. Geological Survey has made available a set of digital elevation maps of 1-degree quadrangles covering the contiguous United States, Hawaii, and limited portions of Alaska. The data is on a regular grid with a spacing of 30 arc-seconds (or about 100-meter resolution). 1-degree DEMs are also referred to as *3-arc-second* or *1:250,000 scale* DEM data.

The data is derived from the U.S. Defense Mapping Agency's DTED-1 digital elevation model, which itself was derived from cartographic and photographic sources. The cartographic sources were maps from the 7.5-minute through 1-degree series (1:24,000 scale through 1:250,000 scale).

Examples

Read every fifth point in the file containing part of Rhode Island and Cape Cod:

```
[Z,refvec] = usgsdem('providence-e',5);
```

Read the elevation data for Martha's Vineyard at full resolution:

```
[Z,refvec] = usgsdem('providence-e',1,...
    [41.2952 41.4826],[-70.8429 -70.4392]);
```

```
whos Z
```

| Name | Size | Bytes | Class |
|------|---------|--------|--------------|
| Z | 226x485 | 876880 | double array |

Tips

The grid for the digital elevation maps is based on the 1984 World Geodetic System (WGS84). Older DEMs were based on WGS72. Elevations are in meters relative to National Geodetic Vertical Datum of 1929 (NGVD 29) in the continental U.S. and local mean sea level in Hawaii.

The absolute horizontal accuracy of the DEMs is 130 meters, while the absolute vertical accuracy is ± 30 meters. The relative horizontal and vertical accuracy is not specified, but is probably much better than the absolute accuracy.

These DEMs have a grid spacing of 3 arc-seconds in both the latitude and longitude directions. The exception is DEM data in Alaska, where latitudes between 50 and 70 degrees North have grid spacings of 6 arc-seconds, and latitudes greater than 70 degrees North have grid spacings of 9 arc-seconds.

Statistical data in the files is not returned.

You can obtain the data files from the U.S. Geological Survey and from commercial vendors. Other agencies have made some local area data available online.

Note For details on locating map data for download over the Internet, see the following documentation at the MathWorks Web site: "Find Geospatial Data Online".

See Also

etopo | gtopo30 | tbase | usgs24kdem | usgsdems

Introduced before R2006a

usgsdems

USGS 1-degree (3-arc-sec) DEM filenames for latitude-longitude quadrangle

Syntax

```
[fname,qname] = usgsdems(latlim,lonlim)
```

Description

[fname,qname] = usgsdems(latlim,lonlim) returns cell arrays of the DEM filenames and quadrangle names covering the geographic region. The region is specified by scalar latitude and longitude points or two-element vectors of latitude and longitude limits in units of degrees.

Background

The U.S. Geological Survey has made available a set of digital elevation maps of 1-degree quadrangles covering the contiguous United States, Hawaii, and limited portions of Alaska. These are referred to as *1-degree, 3-arc second* or *1:250,000 scale* DEMs. Because the filenames of these 1 degree data sets are taken from the names of cities or features in the quadrangle, determining the files needed to cover a particular region generally requires consulting an index map or other reference. This function takes the place of such a reference by returning the filenames for a given geographic region.

Examples

Which files are needed to map part of New England?

```
usgsdems([41 44], [-72 -69])
```

```
ans =  
    'providence-w'  
    'providence-e'
```

```
'chatham-w'  
'boston-w'  
'boston-e'  
'portland-w'  
'portland-e'  
'bath-w'
```

Tips

This function only returns filenames for the contiguous United States.

See Also

usgsdem

Introduced before R2006a

utmgeoid

Select ellipsoids for given UTM zone

Syntax

```
ellipsoid = utmgeoid  
ellipsoid = utmgeoid(zone)  
[ellipsoid,ellipsoidstr] = utmgeoid(...)
```

Description

The purpose of this function is to recommend a local ellipsoid for use with a given UTM zone, depending on the geographic location of that zone. Use it only if you are not using a global reference ellipsoid, such as the World Geodetic System (WGS) 1984 ellipsoid. In many cases, depending on your application, you should just use the output of `wgs84Ellipsoid`, or one of the other options available through `referenceEllipsoid`.

`ellipsoid = utmgeoid`, without any arguments, opens the `utmzoneui` interface for selecting a UTM zone. This zone is then used to return the recommended ellipsoid definitions for that particular zone.

`ellipsoid = utmgeoid(zone)` uses the input `zone` to return the recommended ellipsoid definitions.

`[ellipsoid,ellipsoidstr] = utmgeoid(...)` returns the short name(s) for the reference ellipsoid(s), as used by `referenceEllipsoid`, in a char array with one name in each row.

Background

The Universal Transverse Mercator (UTM) system of projections tiles the world into quadrangles called zones. Each zone has different projection parameters and commonly used ellipsoidal models of the Earth. This function returns a list of ellipsoid models commonly used in a zone.

Examples

```
zone = utmzone(0,100) % degrees
```

```
zone =  
47N
```

```
[ellipsoid,names] = utmgeoid(zone)
```

```
ellipsoid =  
    6377.3    0.081473  
    6377.4    0.081697
```

```
names =  
everest  
bessel
```

See Also

[referenceEllipsoid](#) | [wgs84Ellipsoid](#)

Introduced before R2006a

utmzone

Select UTM zone given latitude and longitude

Syntax

```
zone = utmzone
zone = utmzone(lat, long)
zone = utmzone(mat),
[latlim, lonlim] = utmzone(zone)
lim = utmzone(zone)
```

Description

`zone = utmzone` selects a Universal Transverse Mercator (UTM) zone with a graphical user interface. Returns the UTM zone designation as a character vector.

`zone = utmzone(lat, long)` returns the UTM zone containing the geographic coordinates. If `lat` and `long` are vectors, the zone containing the geographic mean of the data set is returned. The geographic coordinates must be in units of degrees.

`zone = utmzone(mat)`, where `mat` is of the form `[lat long]`.

`[latlim, lonlim] = utmzone(zone)` returns the geographic limits of the zone, where `zone` is a valid UTM zone designation. Valid UTM zones designations are numbers, or numbers followed by a single letter. For example, '31' or '31N'. The returned limits are in units of degrees.

`lim = utmzone(zone)` returns the limits in a single vector output.

Background

The Universal Transverse Mercator (UTM) system of projections tiles the world into quadrangles called zones. This function can be used to identify which zone is used for a geographic area and, conversely, what geographic limits apply to a UTM zone.

Examples

```
[latlim,lonlim] = utmzone('12F')
```

```
latlim =  
    -56    -48  
lonlim =  
   -114   -108
```

```
utmzone(latlim,lonlim)
```

```
ans =  
12F
```

Limitations

The UTM zone system is based on a regular division of the globe, with the exception of a few zones in northern Europe. `utmzone` does not account for these deviations.

See Also

`utmgeoid`

Introduced before R2006a

validateLengthUnit

Validate and standardize length unit

Syntax

```
standardName = validateLengthUnit(unit)
standardName = validateLengthUnit(unit, funcName, varName, argIndex)
```

Description

`standardName = validateLengthUnit(unit)` checks that `unit` is a valid length unit and converts it to a standard unit name. The function is case-insensitive with respect to its input. Spaces, periods, and apostrophes are ignored. Plural forms are accepted in most cases, but the result, `standardName` is always singular.

`standardName = validateLengthUnit(unit, funcName, varName, argIndex)` checks that `unit` is a valid length unit and, if it isn't, creates an error message using the optional inputs `funcName`, `varName`, and `argIndex` in error message formatting, with behavior identical to that provided by the `validateattributes` inputs of the same names.

Examples

Find Valid Length Unit Name

Find the valid length unit name for 'foot' when other valid strings for 'foot' are input.

```
validateLengthUnit('foot')
ans =
'foot'
validateLengthUnit('feet')
```

```
ans =  
'foot'
```

```
validateLengthUnit('international feet')
```

```
ans =  
'foot'
```

Find the valid length unit name for 'kilometer' when other valid strings for 'kilometer' are input.

```
validateLengthUnit('kilometer')
```

```
ans =  
'kilometer'
```

```
validateLengthUnit('km')
```

```
ans =  
'kilometer'
```

```
validateLengthUnit('kilometre')
```

```
ans =  
'kilometer'
```

```
validateLengthUnit('kilometers')
```

```
ans =  
'kilometer'
```

```
validateLengthUnit('kilometres')
```

```
ans =  
'kilometer'
```

Find the valid length unit name when the name contains an apostrophe.

```
validateLengthUnit('Clarke's foot')
```

```
ans =  
'Clarke's foot'
```


Create Custom Error Message

Create custom error messages using the `validateLengthUnit` function. An invalid input to `validateLengthUnit` results in an error message referencing a function name, 'F00', a variable name, 'UNIT' and an argument number, 5.

```
validateLengthUnit(17, 'F00', 'UNIT', 5)
```

```
Error using F00
```

```
Expected input number 5, UNIT, to be one of these types:
```

```
char, string
```

```
Instead its type was double.
```

```
Error in validateLengthUnit (line 87)
```

```
validateattributes(unit,{'char','string'},{'nonempty','scalartext'},varargin{:})
```

Input Arguments

unit – Length unit

character vector | string scalar

Length unit, specified as any of the following:

| Unit Name | Value(s) |
|---------------|---|
| meter | 'm', 'meter(s)', 'metre(s)' |
| centimeter | 'cm', 'centimeter(s)', 'centimetre(s)' |
| millimeter | 'mm', 'millimeter(s)', 'millimetre(s)' |
| micron | 'micron(s)' |
| kilometer | 'km', 'kilometer(s)', 'kilometre(s)' |
| nautical mile | 'nm', 'naut mi', 'nautical mile(s)' |

| Unit Name | Value(s) |
|---------------------------------|---|
| foot | 'ft', 'international ft', 'foot', 'international foot', 'feet', 'international feet' |
| inch | 'in', 'inch', 'inches' |
| yard | 'yd', 'yds', 'yard(s)' |
| mile | 'mi', 'mile(s)', 'international mile(s)' |
| U.S. survey foot | 'sf', 'survey ft', 'US survey ft', 'U.S. survey ft', 'survey foot', 'US survey foot', 'U.S. survey foot', 'survey feet', 'US survey feet', 'U.S. survey feet' |
| U.S. survey mile (statute mile) | 'sm', 'survey mile(s)', 'statute mile(s)', 'US survey mile(s)', 'U.S. survey mile(s)' |
| Clarke's foot | 'Clarke's foot', 'Clarkes foot' |
| German legal metre | 'German legal metre', 'German legal meter' |
| Indian foot | 'Indian foot' |

Example: `validateLengthUnit('feet')`

Data Types: `char` | `string`

funcName — Name of the function whose input you are validating

`character vector` | `string scalar`

Name of the function whose input you are validating, specified as a string scalar or character vector. If you specify an empty string or character vector (''), the `validateLengthUnit` function ignores the `funcName` value.

Example: `validateLengthUnit(17, 'F00', 'UNIT', 5)`

Data Types: `char` | `string`

varName — Name of input variable

character vector | string scalar

Name of input variable, specified as a string scalar or character vector. If you specify an empty string or character vector (''), the validateLengthUnit function ignores the varName value.

Example: validateLengthUnit(17, 'F00', 'UNIT', 5)

Data Types: char | string

argIndex — Position of the input argument

positive integer

Position of the input argument, specified as a positive integer.

Example: validateLengthUnit(17, 'F00', 'UNIT', 5)

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64

Output Arguments

standardName — Standard length unit name

character vector

Standard length unit name, returned as a character vector.

See Also

unitsratio

Introduced before R2006a

vec2mtx

Convert latitude-longitude vectors to regular data grid

Syntax

```
[Z, R] = vec2mtx(lat, lon, density)
[Z, R] = vec2mtx(lat, lon, density, latlim, lonlim)
[Z, R] = vec2mtx(lat, lon, Z1, R1)
[Z, R] = vec2mtx(..., 'filled')
```

Description

`[Z, R] = vec2mtx(lat, lon, density)` creates a regular data grid `Z` from vector data, placing ones in grid cells intersected by a vector and zeroes elsewhere. `R` is the referencing vector for the computed grid. `lat` and `lon` are vectors of equal length containing geographic locations in units of degrees. `density` indicates the number of grid cells per unit of latitude and longitude (a value of 10 indicates 10 cells per degree, for example), and must be scalar-valued. Whenever there is space, a buffer of two grid cells is included on each of the four sides of the grid. The buffer is reduced as needed to keep the latitudinal limits within [-90 90] and to keep the difference in longitude limits from exceeding 360 degrees.

`[Z, R] = vec2mtx(lat, lon, density, latlim, lonlim)` uses the two-element vectors `latlim` and `lonlim` to define the latitude and longitude limits of the grid.

`[Z, R] = vec2mtx(lat, lon, Z1, R1)` uses a pre-existing data grid `Z1`, georeferenced by `R1`, to define the limits and density of the output grid. `R1` can be a referencing vector, a referencing matrix, or a geographic raster reference object.

If `R1` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z1)` and its `RasterInterpretation` must be `'cells'`.

If `R1` is a referencing vector, it must be a 1-by-3 vector containing elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

or a 3-by-2 referencing matrix that transforms raster row and column indices to/from geographic coordinates according to:

```
[lon lat] = [row col 1] * R1
```

If `R1` is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. With this syntax, output `R` is equal to `R1`, and may be a referencing object, vector, or matrix.

`[Z, R] = vec2mtx(..., 'filled')`, where `lat` and `lon` form one or more closed polygons (with NaN-separators), fills the area outside the polygons with the value two instead of the value zero.

Notes

Empty `lat`, `lon` vertex arrays will result in an error unless the grid limits are explicitly provided (via `latlim`, `lonlim` or `Z1`, `R1`). In the case of explicit limits, `Z` will be filled entirely with 0s if the `'filled'` parameter is omitted, and 2s if it is included.


It's possible to apply `vec2mtx` to sets of polygons that tile without overlap to cover an area, as in Example 1 below, but using `'filled'` with polygons that actually overlap may lead to confusion as to which areas are inside and which are outside.

Examples

Example 1

Convert latitude-longitude polygons to a regular data grid and display as a map.


```
states = shaperead('usastatelo', 'UseGeoCoords', true);
lat = [states.Lat];
lon = [states.Lon];
[Z, R] = vec2mtx(lat, lon, 5, 'filled');
figure; worldmap(Z, R);
geoshow(Z, R, 'DisplayType', 'texturemap')
colormap(flag(3))
```



Example 2

Combine two separate calls to `vec2mtx` to create a 4-color raster map showing interior land areas, coastlines, oceans, and world rivers.

```
load coastlines
[Z, R] = vec2mtx(coastlat, coastlon, ...
    1, [-90 90], [-90 270], 'filled');
rivers = shaperead('worldrivers.shp', 'UseGeoCoords', true);
A = vec2mtx([rivers.Lat], [rivers.Lon], Z, R);
Z(A == 1) = 3;
figure; worldmap(Z, R)
geoshow(Z, R, 'DisplayType', 'texturemap')
colormap([.45 .60 .30; 0 0 0; 0 0.5 1; 0 0 1])
```



Define Limits and Density of Output Grid Using Spatial Referencing Object

Import US state outlines.

```
states = shaperead('usastatelo', 'UseGeoCoords', true);
lat = [states.Lat];
lon = [states.Lon];
```

Choose geographic limits.

```
latlim = [ 15 75];
lonlim = [-190 -65];
```

Specify a grid with 5 cells per degree.

```
density = 5;
```

Compute raster size. (M and N both work out to be integers.)

```
M = density * diff(latlim);
N = density * diff(lonlim);
```

Construct a Geographic Raster Reference object.

```
R = georasterref('RasterSize', [M N], ...
    'ColumnsStartFrom', 'north', 'Latlim', latlim, ...
    'Lonlim', lonlim);
```

Create a blank grid that is consistent with R in size. `vec2mtx` requires a data grid as input.


```
Z = zeros(R.RasterSize);
```

Overwrite Z with a new grid including state outlines and interiors.

```
Z = vec2mtx(lat, lon, Z, R, 'filled');
```

Plot the georeferenced grid.

```
figure; worldmap(Z, R);
geoshow(Z, R, 'DisplayType', 'texturemap')
colormap(flag(3))
```



See Also

`imbedm`

Introduced before R2006a

vertcat

Vertically concatenate geographic or planar vectors

Syntax

```
v = vertcat(v1,v2,...)
```

Description

`v = vertcat(v1,v2,...)` vertically concatenates the geographic or planar vectors `v1`, `v2`, and so on. If the class type of any property is a cell array, then the resultant field in the output `v` is also a cell array.

Examples

Vertically Concatenate Mapshape Vectors

Create three mapshape vectors. The second vector has two features and is size 2x1.

```
ms1 = mapshape(42, -110, 'Temperature', 65, 'Name', 'point1');  
ms2 = mapshape({50, 50.1}, {-101 -101.4}, 'Temperature', {73.2 77}, 'Name', {'point2',  
ms3 = mapshape(42.1, -110.4, 'Temperature', 65.5, 'Name', 'point4');
```

Vertically concatenate the vectors into a single mapshape vector.

```
ms = vertcat(ms1, ms2, ms3)
```

```
ms =
```

```
4x1 mapshape vector with properties:
```

```
Collection properties:
```

```
    Geometry: 'line'
```

```
    Metadata: [1x1 struct]
```

```
Vertex properties:
```

```
(4 features concatenated with 3 delimiters)
```

```
X: [42 NaN 50 NaN 50.1000 NaN 42.1000]
Y: [-110 NaN -101 NaN -101.4000 NaN -110.4000]
Temperature: [65 NaN 73.2000 NaN 77 NaN 65.5000]
Feature properties:
  Name: {'point1' 'point2' 'point3' 'point4'}
```

The concatenated mapshape vector `ms` is size 4x1 and has four features. Note that the property 'Temperature' is a Vertex property in `ms` because it is a Vertex property in `ms2`, even though it is a Feature property in `ms1` and `ms3`.

Input Arguments

`v1, v2, ...` — Geographic or planar vectors to be concatenated

`geopoint`, `geoshape`, `mappoint`, or `mapshape` objects

Geographic or planar vectors to be concatenated, specified as one or many `geopoint`, `geoshape`, `mappoint`, or `mapshape` objects. All of `v1`, `v2`,... are the same type of object.

Output Arguments

`v` — Concatenated geographic or planar vector

`geopoint`, `geoshape`, `mappoint`, or `mapshape` object

Concatenated geographic or planar vector, returned as a `geopoint`, `geoshape`, `mappoint`, or `mapshape` object. The object type of `v` matches the object type of `v1, v2, ...`.

See Also

`cat`

Introduced in R2012a

vfdtran

Direction angle in map plane from azimuth on ellipsoid

Syntax

```
th = vfdtran(lat,lon,az)
th = vfdtran(mstruct,lat,lon,az)
[th,len] = vfdtran(...)
```

Description

`th = vfdtran(lat,lon,az)` transforms the azimuth angle at specified latitude and longitude points on the sphere into the projection space. The map projection currently displayed is used to define the projection space. The input angles must be in the same units as specified by the current map projection. The inputs can be scalars or matrices of the equal size. The angle in the projection space is defined as positive counterclockwise from the x -axis.

`th = vfdtran(mstruct,lat,lon,az)` uses the map projection defined by the input `mstruct` to compute the map projection.

`[th,len] = vfdtran(...)` also returns the vector length in the projected coordinate system. A value of 1 indicates no scale distortion.


Background

The direction of north is easy to define on the three-dimensional sphere, but more difficult on a two-dimensional map. For cylindrical projections in the normal aspect, north is always in the positive y -direction. For conic projections, north can be to the left or right of the y -axis. This function transforms any azimuth angle on the sphere to the corresponding angle in the projected paper coordinates.

Examples

Sample calculations:

```
axesm('eqdconic','maplatlim',[-10 45],'maplonlim',[-55 55])
gridm; framem; mlabel; plabel
quiverm([0 0 0],[-45 0 45],[0 0 0],[10 10 10],0)
quiverm([0 0 0],[-45 0 45],[10 10 10],[0 0 0],0)
```



```
vfdtran([0 0 0],[-45 0 45],[0 0 0])
```

```
ans =
    59.614         90    120.39
```

```
vfdtran([0 0 0],[-45 0 45],[90 90 90])
```

```
ans =
   -30.385    0.0001931    30.386
```

Limitations

This transformation is limited to the region specified by the frame limits in the current map definition.

Tips

The geographic azimuth angle is measured clockwise from north. The projection space angle is measured counterclockwise from the x -axis.

This function uses a finite difference technique. The geographic coordinates are perturbed slightly in different directions and projected. A small amount of error is introduced by numerical computation of derivatives and the variation of map distortion parameters.

See Also

`defaultm` | `mfwdtran` | `minvtran` | `vinvtran`

Introduced before R2006a

viewshed

Areas visible from point on terrain elevation grid

Syntax

```
[vis,R] = viewshed(Z,R,lat1,lon1)
viewshed(Z,R,lat1,lon1,observerAltitude)
viewshed(Z,R,lat1,lon1,observerAltitude,targetAltitude)
viewshed(Z,R,lat1,lon1,observerAltitude,targetAltitude, ...
    observerAltitudeOption)
viewshed(Z,R,lat1,lon1,observerAltitude,targetAltitude, ...
    observerAltitudeOption,targetAltitudeOption)
viewshed(Z,R,lat1,lon1,observerAltitude,targetAltitude, ...
    observerAltitudeOption,targetAltitudeOption,actualRadius)
viewshed(Z,R,lat1,lon1,observerAltitude,targetAltitude, ...
    observerAltitudeOption,targetAltitudeOption, ...
    actualRadius,effectiveRadius)
```

Description

`[vis,R] = viewshed(Z,R,lat1,lon1)` computes areas visible from a point on a digital elevation grid. `Z` is a regular data grid containing elevations in units of meters. The observer location is provided as scalar latitude and longitude in units of degrees. The visibility grid `vis` contains 1s at the surface locations visible from the observer location, and 0s where the line of sight is obscured by terrain. `R` can be a geographic raster reference object, a referencing vector, or a referencing matrix.

If `R` is a geographic raster reference object, its `RasterSize` property must be consistent with `size(Z)`.

If `R` is a referencing vector, it must be a 1-by-3 with elements:

```
[cells/degree northern_latitude_limit western_longitude_limit]
```

If `R` is a referencing matrix, it must be 3-by-2 and transform raster row and column indices to or from geographic coordinates according to:

```
[lon lat] = [row col 1] * R
```

If *R* is a referencing matrix, it must define a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel. Nearest-neighbor interpolation is used by default. NaN is returned for points outside the grid limits or for which *lat* or *lon* contain NaN. All angles are in units of degrees.

`viewshed(Z,R,lat1,lon1,observerAltitude)` places the observer at the specified altitude in meters above the surface. This is equivalent to putting the observer on a tower. If omitted, the observer is assumed to be on the surface.

`viewshed(Z,R,lat1,lon1,observerAltitude,targetAltitude)` checks for visibility of target points a specified distance above the terrain. This is equivalent to putting the target points on towers that do not obstruct the view. If omitted, the target points are assumed to be on the surface.

`viewshed(Z,R,lat1,lon1,observerAltitude,targetAltitude, ...
observerAltitudeOption)` controls whether the observer is at a relative or absolute altitude. If the `observerAltitudeOption` is 'AGL', then `observerAltitude` is in meters above ground level. If `observerAltitudeOption` is 'MSL', `observerAltitude` is interpreted as altitude above zero, or mean sea level. If omitted, 'AGL' is assumed.

`viewshed(Z,R,lat1,lon1,observerAltitude,targetAltitude, ...
observerAltitudeOption,targetAltitudeOption)` controls whether the target points are at a relative or absolute altitude. If the target altitude option is 'AGL', the `targetAltitude` is in meters above ground level. If `targetAltitudeOption` is 'MSL', `targetAltitude` is interpreted as altitude above zero, or mean sea level. If omitted, 'AGL' is assumed.

`viewshed(Z,R,lat1,lon1,observerAltitude,targetAltitude, ...
observerAltitudeOption,targetAltitudeOption,actualRadius)` does the visibility calculation on a sphere with the specified radius. If omitted, the radius of the earth in meters is assumed. The altitudes, the elevations, and the radius should be in the same units. This calling form is most useful for computations on bodies other than the Earth.

`viewshed(Z,R,lat1,lon1,observerAltitude,targetAltitude, ...
observerAltitudeOption,targetAltitudeOption, ...
actualRadius,effectiveRadius)` assumes a larger radius for propagation of the line of sight. This can account for the curvature of the signal path due to refraction in the

atmosphere. For example, radio propagation in the atmosphere is commonly treated as straight line propagation on a sphere with $4/3$ the radius of the Earth. In that case the last two arguments would be R_e and $4/3*R_e$, where R_e is the radius of the earth. Use `Inf` for flat Earth viewshed calculations. The altitudes, the elevations, and the radii should be in the same units.

Examples

Compute Visibility for Point on Peaks Map

Compute visibility for a point on the peaks map. Add the detailed information for the line of sight calculation between two points from `los2`.


Create the peak map and plot the visibility.

```
Z = 500*peaks(100);
refvec = [1000 0 0];
[lat1,lon1,lat2,lon2] = deal(-0.027,0.05,-0.093,0.042);

[visgrid,visleg] = viewshed(Z,refvec,lat1,lon1,100);
[vis,visprofile,dist,zi,lattrk,lontrk] ...
    = los2(Z,refvec,lat1,lon1,lat2,lon2,100);

axesm('globe','geoid',earthRadius('meters'))
meshm(visgrid,visleg,size(Z),Z);
axis tight
camposm(-10,-10,1e6)
camupm(0,0)
colormap(flipud(summer(2)))
brighten(0.75)
shading interp
camlight
h = lcolorbar({'obscured','visible'});
h.Position = [.875 .45 .02 .1];

plot3m(lattrk([1;end]),lontrk([1; end]), ...
    zi([1; end])+[100; 0],'r','linewidth',2)
plotm(lattrk(~visprofile),lontrk(~visprofile), ...
    zi(~visprofile),'r.','markersize',10)
plotm(lattrk(visprofile),lontrk(visprofile), ...
    zi(visprofile),'g.','markersize',10)
```





Compute Surface Area Visible By Radar

Compute the surface area visible by radar from an aircraft flying 3000 meters above the Yellow Sea. Assume that radio wave propagation in the atmosphere can be modeled as straight lines on a $4/3$ radius Earth. This example also calculates the area visible to the plane above it at 5000 meters.


Load data from the MAT-file containing information about the Korean peninsula, calculate the viewshed, and display it.

```
load korea
map(map<0) = -1;
figure
worldmap(map,refvec)
setm(gca,'geoid',[1 0])
da = daspect;
pba = pbaspect;
da(3) = 7.5*pba(3)/da(3);
daspect(da);
demcmap(map)
camlight(90,5);
camlight(0,5);
lighting gouraud
material([0.25 0.8 0])
lat = 34.0931; lon = 125.6578;
altobs = 3000; alttarg = 0;
plotm(lat,lon,'wo')
Re = earthRadius('meters');
[vmap,vmapl] = viewshed( ...
    map,refvec,lat,lon,altobs,alttarg, ...
    'MSL','AGL',Re,4/3*Re);
meshm(vmap,vmapl,size(map),map)
```




Display the visible areas as blue and the obscured areas as red and drape the visibility colors on an elevation map, using lighting to bring out the surface topography. The aircraft's radar can see out a certain radius on the surface of the ocean, but note how some ocean areas are shadowed by the island of Jeju-Do. Also some mountain valleys closer than the ocean horizon are obscured, while some mountain tops further away are visible.

```
caxis auto; colormap([1 0 0; 0 0 1])  
lighting gouraud;  
axis off
```



Now calculate the area that the radar plane flying at an altitude of 3000 meters can have line-of-sight to other aircraft flying above it at 5000 meters. Note how the area is much larger but that some edges of the area are reduced by shadowing from Jeju-Do and the mountains on the Korean peninsula.

```
[vmap,vmapl] = viewshed(map,refvec,lat,lon,3000,5000, ...  
                        'MSL','MSL',Re,4/3*Re);  
clmo surface  
meshm(vmap,vmapl,size(map),map)  
lighting gouraud
```



Tips

The observer should be located within the latitude-longitude limits of the elevation grid. If the observer is located outside the grid, there is insufficient information to calculate a viewshed. In this case `viewshed` issues a warning and sets all elements of `vis` to zero.

See Also

`los2`

Introduced before R2006a

vinvtran

Azimuth on ellipsoid from direction angle in map plane

Syntax

```
az = vinvtran(x,y,th)
az = vinvtran(mstruct,x,y,th)
[az,len] = vinvtran(...)
```

Description

`az = vinvtran(x,y,th)` transforms an angle in the projection space at the point specified by `x` and `y` into an azimuth angle in geographic coordinates. The map projection currently displayed is used to define the projection space. The input angles must be in the same units as specified by the current map projection. The inputs can be scalars or matrices of equal size. The angle in the projection space angle `th` is defined as positive counterclockwise from the `x`-axis.

`az = vinvtran(mstruct,x,y,th)` uses the map projection defined by the input `struct` to compute the map projection.

`[az,len] = vinvtran(...)` also returns the vector length in the geographic coordinate system. A value of 1 indicates no scale distortion for that angle.


Background

While vectors along the `y`-axis always point to north in a cylindrical projection in the normal aspect, they can point east or west of north on conics, azimuthals, and other projections. This function computes the geographic azimuth for angles in the projected space.

Examples

Sample calculations:

```
axesm('eqdconic','maplatlim',[-10 45],'maplonlim',[-55 55])
gridm; framem; mlabel; plabel
[x,y] = mfwdtran([0 0 0],[-45 0 45]);
quiver(x,y,[.2 .2 .2],[0 0 0],0)
quiver(x,y,[0 0 0],[.2 .2 .2],0)
```



```
vinvtran(x,y,[ 0 0 0])
```

```
ans =
    57.345    90.338   124.98
```

```
vinvtran(x,y,[ 90 90 90])
```

```
ans =
    331.99         0    28.008
```

Limitations

This transformation is limited to the region specified by the frame limits in the current map definition.

Tips

The geographic azimuth angle is measured clockwise from north. The projection space angle is measured counterclockwise from the x -axis.

This function uses a finite difference technique. The geographic coordinates are perturbed slightly in different directions and projected. A small amount of error is introduced by numerical computation of derivatives and the variation of map distortion parameters.

See Also

`defaultm` | `mfwdtran` | `minvtran` | `vfwdtran`

Introduced before R2006a

vmap0data

Read selected data from Vector Map Level 0

Syntax

```
struct = vmap0data(library,latlim,lonlim,theme,topolevel)
struct = vmap0data(devicename,library, ...)
[struct1, struct2, ...] = vmap0data(...,{topolevel1,topolevel2,...})
```

Description

`struct = vmap0data(library,latlim,lonlim,theme,topolevel)` reads the data for the specified theme and topology level directly from the VMAP0 CD-ROM. There are four CDs, one for each of the libraries: 'NOAMER' (North America), 'SAS AUS' (Southern Asia and Australia), 'EURNASIA' (Europe and Northern Asia), and 'SOAMAFR' (South America and Africa). The desired `theme` is specified by a two-letter code. A list of valid codes is displayed when an invalid code, such as '?', is entered. `topolevel` defines the type of data returned: 'patch', 'line', 'point', or 'text'. The region of interest can be given as a point latitude and longitude or as a region with two-element vectors of latitude and longitude limits. The units of latitude and longitude are degrees. The data covering the requested region is returned, but will include data extending to the edges of the tiles. The result is returned as a Mapping Toolbox Version 1 display structure.

`struct = vmap0data(devicename,library, ...)` specifies the logical device name of the CD-ROM for computers that do not automatically name the mounted disk.

`[struct1, struct2, ...] = vmap0data(...,{topolevel1,topolevel2,...})` reads several topology levels. The levels must be specified as a cell array with the entries 'patch', 'line', 'point', or 'text'. Entering {'all'} for the topology level argument is equivalent to {'patch', 'line', 'point', 'text'}. Upon output, the data structures are returned in the output arguments by topology level in the same order as they were requested.

Background

The Vector Map (VMAP) Level 0 database represents the third edition of the *Digital Chart of the World*. The second edition was a limited release item published in 1995. The product is dual named to show its lineage to the original DCW, published in 1992, while positioning the revised product within a broader emerging family of VMAP products. VMAP Level 0 is a comprehensive 1:1,000,000 scale vector base map of the world. It consists of cartographic, attribute, and textual data stored on compact disc read-only memory (CD-ROM). The primary source for the database is the Operational Navigation Chart (ONC) series of the U. S. National Geospatial Intelligence Agency (NGA), formerly the National Imagery and Mapping Agency (NIMA), and before that, the Defense Mapping Agency (DMA). This is the largest scale unclassified map series in existence that provides consistent, continuous global coverage of essential base map features. The database contains more than 1,900 MB of vector data and is organized into 10 thematic layers. The data includes major road and rail networks, major hydrologic drainage systems, major utility networks (cross-country pipelines and communication lines), all major airports, elevation contours (1000 foot (ft), with 500 ft and 250 ft supplemental contours), coastlines, international boundaries, and populated places. The database can be accessed directly from the four optical CD-ROMs that store the database or can be transferred to magnetic media.

Examples

The *devicename* is platform dependent. On an MS-DOS based operating system it would be something like 'd:', depending on the logical device code assigned to the CD-ROM drive. On a UNIX operating system, the CD-ROM might be mounted as '\cdrom', '\CDROM', '\cdrom1', or something similar. Check your computer's documentation for the right *devicename*.

```
s = vmap0data(devicename,'NOAMER',41,-69,'?','patch');
```

```
??? Error using ==> vmap0data
Theme not present in library NOAMER
```

```
Valid theme identifiers are:
libref : Library Reference
tileref: Tile Reference
bnd    : Boundaries
dq     : Data Quality
elev   : Elevation
```

```
hydro : Hydrography
ind   : Industry
phys  : Physiography
pop   : Population
trans : Transportation
util  : Utilities
veg   : Vegetation
```

```
BNDpatch = vmap0data(devicename,'NOAMER',...
                [41 44],[-72 -69],'bnd','patch')
```

```
BNDpatch =
1x169 struct array with fields:
    type
    otherproperty
    altitude
    lat
    long
    tag
```

Here are other examples:

```
[TRtext,TRline] = vmap0data(devicename,'SASAU',...
    [-48 -34],[164 180],'trans',{'text','line'});
```

```
[BNDpatch,BNDline,BNDpoint,BNDtext] = vmap0data(devicename,...
    'EURASIA',-48 ,164,'bnd',{'all'});
```

Tips

Data are returned as Mapping Toolbox display structures, which you can then update to geographic data structures. For information about display structure format, see “Version 1 Display Structures” on page 1-257 in the reference page for `displaym`. The `updategeosstruct` function performs such conversions.

Latitudes and longitudes use WGS84 as a horizontal datum. Elevations and depths are in meters above mean sea level.

Some VMAP0 themes do not contain all topology levels. In those cases, empty matrices are returned.

Patches are broken at the tile boundaries. Setting the `EdgeColor` to `'none'` and plotting the lines gives the map a normal appearance.

The major differences between VMAP0 and the DCW are the elimination of the gazette layer, addition of bathymetric data, and updated political boundaries.

Vector Map Level 0, created in the 1990s, is still probably the most detailed global database of vector map data available to the public. VMAP0 CD-ROMs are available from through the U.S. Geological Survey (USGS):

USGS Information Services (Map and Book Sales)
Box 25286
Denver Federal Center
Denver, CO 80225
Telephone: (303) 202-4700
Fax: (303) 202-4693

Note For details on locating map data for download over the Internet, see the following documentation at the MathWorks Web site: “Find Geospatial Data Online”.

See Also

`extractm` | `geoshow` | `mlayers` | `updategeostruct` | `vmap0read` | `vmap0rhead`

Introduced before R2006a

vmap0read

Read Vector Map Level 0 file

Syntax

```
vmap0read  
vmap0read(filepath, filename)  
vmap0read(filepath, filename, recordIDs)  
vmap0read(filepath, filename, recordIDs, field, varlen)  
struc = vmap0read(...)  
[struc, field] = vmap0read(...)  
[struc, field, varlen] = vmap0read(...)  
[struc, field, varlen, description] = vmap0read(...)  
[struc, field, varlen, description, narrativefield] = vmap0read(...)
```

Description

`vmap0read` reads a VMAP0 file. The user selects the file interactively.

`vmap0read(filepath, filename)` reads the specified file. The combination `[filepath filename]` must form a valid complete filename.

`vmap0read(filepath, filename, recordIDs)` reads selected records or fields from the file. If `recordIDs` is a scalar or a vector of integers, the function returns the selected records. If `recordIDs` is a cell array of integers, all records of the associated fields are returned.

`vmap0read(filepath, filename, recordIDs, field, varlen)` uses previously read field and variable-length record information to skip parsing the file header (see below).

`struc = vmap0read(...)` returns the file contents in a structure.

`[struc, field] = vmap0read(...)` returns the file contents and a structure describing the format of the file.

[struc, field, varlen] = vmap0read(...) also returns a vector describing which fields have variable-length records.

[struc, field, varlen, description] = vmap0read(...) also returns description, a character vector that describes the contents of the file.

[struc, field, varlen, description, narrativefield] = vmap0read(...) also returns the name of the narrative file for the current file.

Background

The Vector Map Level 0 (VMAPO) uses binary files in a variety of formats. This function determines the format of the file and returns the contents in a structure. The field names of this structure are the same as the field names in the VMAPO file.

Examples

The following examples use the UNIX directory system and file separators for the pathname:

```
s = vmap0read('VMAP/VMAPLV0/NOAMER/', 'GRT')
```

```
s =
      id: 1
    data_type: 'GEO'
      units: 'M'
  ellipsoid_name: 'WGS 84'
ellipsoid_detail: 'A=6378137 B=6356752 Meters'
  vert_datum_name: 'MEAN SEA LEVEL'
  vert_datum_code: '015'
  sound_datum_name: 'N/A'
  sound_datum_code: 'N/A'
    geo_datum_name: 'WGS 84'
    geo_datum_code: 'WGE'
  projection_name: 'Dec. Deg. (unproj.)'
```

```
s = vmap0read('VMAP/VMAPLV0/NOAMER/TRANS/', 'INT.VDT')
```

```
s =
34x1 struct array with fields:
```

```
    id
    table
    attribute
    value
    description

s(1)

ans =
        id: 1
        table: 'aerofacp.pft'
        attribute: 'use'
        value: 8
        description: 'Military'
s = vmap0read('VMAP/VMAPLV0/NOAMER/TRANS/', 'AEROFACP.PFT', 1)

s =
        id: 1
        f_code: 'GB005'
        iko: 'BGTL'
        nam: 'THULE AIR BASE'
        na3: 'GL52085'
        use: 8
        zv3: 77
        tile_id: 10
        end_id: 1

s = vmap0read('VMAP/VMAPLV0/NOAMER/TRANS/', 'AEROFACP.PFT', {1,2})

s =
1x4424 struct array with fields:
    id
    f_code
```

Tips

This function reads all VMAP0 files except index files (files with names ending in 'X'), thematic index files (files with names ending in 'TI'), and spatial index files (files with names ending in 'SI').

File separators are platform dependent. The *filepath* input must use appropriate file separators, which you can determine using the MATLAB `filesep` function.

See Also

vmap0data | vmap0rhead

Introduced before R2006a

vmap0rhead

Read Vector Map Level 0 file headers

Syntax

```
vmap0rhead  
vmap0rhead(filepath, filename)  
vmap0rhead(filepath, filename, fid)  
vmap0rhead(...),  
str = vmap0rhead(...)
```

Description

`vmap0rhead` allows the user to select the header file interactively.

`vmap0rhead(filepath, filename)` reads from the specified file. The combination `[filepath filename]` must form a valid complete filename.

`vmap0rhead(filepath, filename, fid)` reads from the already open file associated with `fid`.

`vmap0rhead(...)`, with no output arguments, displays the formatted header information on the screen.

`str = vmap0rhead(...)` returns a character vector containing the VMAP0 header.

Background

The Vector Map Level 0 (VMAP0) uses the header in most files to document the contents and format of that file. This function reads the header and displays a formatted version in the Command Window, or returns it as a character vector.

Examples

The following example uses UNIX file separators and pathname:

```
s = vmap0rhead('VMAP/VMAPLV0/NOAMER/', 'GRT')
s =
L;Geographic Reference Table;-;id=I,1,P,Row
Identifier,-,-,-,:data_type=T,3,N,Data
Type,-,-,-,:units=T,3,N,Units of Measure Code for
Library,-,-,-,:ellipsoid_name=T,15,N,Ellipsoid,-,-,-,:ellipsoid
_detail=T,50,N,Ellipsoid
Details,-,-,-,:vert_datum_name=T,15,N,Datum Vertical
Reference,-,-,-,:vert_datum_code=T,3,N,Vertical Datum
Code,-,-,-,:sound_datum_name=T,15,N,Sounding
Datum,-,-,-,:sound_datum_code=T,3,N,Sounding Datum
Code,-,-,-,:geo_datum_name=T,15,N,Datum Geodetic
Name,-,-,-,:geo_datum_code=T,3,N,Datum Geodetic
Code,-,-,-,:projection_name=T,20,N,Projection Name,-,-,-,;;

vmap0rhead('VMAP/VMAPLV0/NOAMER/TRANS/', 'AEROFACP.PFT')
L
Airport Point Feature Table
aerofacp.doc
id=I,1,P,Row Identifier,-,-,-,
f_code=T,5,N,FACC Feature Code,char.vdt,-,-,
iko=T,4,N,ICAO Designator,char.vdt,-,-,
nam=T,*N,Name,char.vdt,-,-,
na3=T,*N,Name,char.vdt,-,-,
use=S,1,N,Usage,int.vdt,-,-,
zv3=S,1,N,Airfield/Aerodrome Elevation (meters),int.vdt,-,-,
tile_id=S,1,N,Tile Reference ID,-,tile1_id.pti,-,
end_id=I,1,N,Entity Node Primitive ID,-,end1_id.pti,-,
```

Tips

This function reads all VMAP0 files except index files (files with names ending in 'X'), thematic index files (files with names ending in 'TI') and spatial index files (files with names ending in 'SI').

File separators are platform dependent. The *filepath* input must use appropriate file separators, which you can determine using the MATLAB filesep function.

See Also

`vmap@data` | `vmap@read`

Introduced before R2006a

webmap

Open web map

Syntax

```
webmap
webmap(baseLayer)
webmap( ____, Name, Value)
wm = webmap( ____ )
webmap(wm)
```

Description

`webmap` opens a new web map in a browser, centering the map at the latitude, longitude point $[0\ 0]$. By default, `webmap` sets the base layer to World Street Map at the maximum spatial extent available. After the web map opens, you can select a different base layer using the Layer Manager available on the right side of the web map. Named base layers are tiled at discrete zoom resolutions.

Note The `webmap` function requires an Internet connection. MathWorks cannot guarantee the stability and accuracy of web maps, as the servers are located on the Internet and are independent from MathWorks. Occasionally, maps may be slow to display, display partially, or fail to display, because web map servers can become unavailable for short periods of time.

`webmap(baseLayer)` opens a new web map with base layer specified by `baseLayer`. `baseLayer` can be one of a list of named Web Map Service providers or a `WMSLayer` array. If `baseLayer` is a matrix of `WMSLayer` objects, `webmap` uses each object's `LayerTitle` property as the value of items in the Layer Manager.

`webmap` displays named base layers in the Web Mercator map coordinate reference system. `webmap` displays `WMSLayers` in the Web Mercator map coordinate reference system, if that projection (EPSG:900913) is available for all layers in the array. Otherwise, `webmap` displays `WMSLayers` in the EPSG:4326 geographic coordinate reference system.

When displaying a `WMSLayer` in the EPSG:4326 geographic coordinate reference system, `webmap` does not include the named base layers in the Layer Manager, because they are in a different coordinate reference system. These projections include a geographic quadrangle bounded north and south by parallels (which map to horizontal lines) and east and west by meridians (which map to vertical lines).

`webmap(____, Name, Value)` opens a new web map with additional display properties set.

`wm = webmap(____)` returns a handle to a web map, `wm`.


`webmap(wm)` makes the web map specified by `wm` the current web map.

Examples

Display a Web map


Open a web map centered at `[0 0]`.

```
webmap
```



To view the list of available base maps, click the expander arrow on the right side of the image.


```
webmap('Light Gray Canvas Map', 'WrapAround', false)
```



Display a Web map with a WMS Layer as the Base Layer


Open a web map and retrieve the Blue Marble WMS layer.

```
nasa = wmsfind('nasa', 'SearchField', 'serverurl');  
baselayer = refine(nasa, 'bluemarbleng', ...
```

```
        'SearchField', 'layername', ...  
        'MatchType', 'exact');  
baselayer = wmsupdate(baselayer);
```

Display a web map with the Blue Marble WMS layer as the base layer.

```
webmap(baselayer)
```



Input Arguments

baseLayer — Map displayed in web map browser

character vector | string scalar | WMSLayer array

Map displayed in web map browser, specified as a string scalar or character vector, listed in the following table, or a WMSLayer array. If specified as string scalar or character vector, the value is case insensitive and spaces are optional.

| Name | Description |
|-------------------------------|---|
| 'World Street Map' | Worldwide street map provided by ESRI. For information about the ESRI ArcGIS Online layers, visit http://www.arcgis.com/home/gallery.html#c=esri&f=basemaps&t=maps . |
| 'Open Street Map' | Street map from openstreetmap.org . For more information, visit http://www.openstreetmap.org . |
| 'World Imagery' | Worldwide imagery provided by ESRI. |
| 'World Topographic Map' | Topographic map for the world from ESRI. |
| 'World Shaded Relief' | Surface elevation as shaded relief provided by ESRI |
| 'World Physical Map' | Natural Earth map of the world provided by ESRI |
| 'World Terrain Base' | Shaded relief and bathymetry provided by ESRI |
| 'USGS Imagery' | Composite of Blue Marble, NAIP, and Landsat provided by the USGS. |
| 'USGS Topographic Imagery' | Topographic map with imagery provided by the USGS. |
| 'USGS Shaded Topographic Map' | Composite of contours, shaded relief, and vector layers provided by the USGS. |
| 'USGS Shaded Relief' | Shaded relief from National Elevation Dataset provided by the USGS. |
| 'National Geographic Map' | General reference map provided by ESRI |
| 'DeLorme World Basemap' | Topographic map provided by ESRI |
| 'Ocean Basemap' | Bathymetry, marine features, depth in meter provided by ESRI |
| 'World Navigation Charts' | Topographic data with nautical information provided by ESRI |
| 'Light Gray Canvas Map' | Neutral background map with minimal colors provided by ESRI |

Data Types: `char` | `string`

wm — Web map

web map handle

Web map, specified as a web map handle, returned by the `webmap` function.

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, . . . , NameN, ValueN`.

Example: `webmap('Light Gray Canvas Map', 'WrapAround', false)`

WrapAround — Control map wrapping

`true` (default) | `false`

Control map wrapping, specified as a logical value `true` (1) or `false` (0). If `true`, the map supports continuous pan and zoom across the 180-degree meridian, but zoom is constrained to show less than 180 degrees of longitude at a time. If `false`, the map is clipped to the west at -180 and clipped to the east at +180, and zoom can be set to show the full extent of the world.

Data Types: `double` | `logical`

Output Arguments

wm — Web map

web map handle

Web map, returned as a web map handle.

Definitions

Web Map

An interactive map accessed through a web page.

In a web map, a user can select different map layers to view and navigate around the map using interactive tools, such as zooming. The web map browser is a window that displays map base layers obtained from Web servers located on the Internet. You can also display overlay layers that contain custom point and line vector data.

Tips

- Particular maps may not support every available zoom level. If your map displays as completely white, try another zoom level. The map you are displaying may not support the zoom level you have currently selected. You can also select another base layer, which might support the specified zoom level.

See Also

`wmcenter` | `wmclose` | `wmlimits` | `wmline` | `wmmarker` | `wmprint` | `wmremove` | `wmzoom`

Introduced in R2013b

WebMapServer

Web map server

Description

A `WebMapServer` object represents a Web Map Service (WMS) and acts as a proxy to a WMS server.

The `WebMapServer` object resides physically on the client side. The object can access the capabilities document on the WMS server and perform requests to obtain maps. It supports multiple WMS versions and negotiates with the server automatically to use the highest known version that the server can support.

Creation

```
server = WebMapServer(serverURL)
```

Description

`server = WebMapServer(serverURL)` creates a `WebMapServer` object, setting the `ServerURL` property.

Properties

Timeout — Number of milliseconds before a server times out

0 (default) | nonnegative integer

Number of milliseconds before a server times out, specified as a nonnegative integer. When `Timeout` has a value of 0, the `WebMapServer` object ignores the timeout mechanism.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64`

EnableCache — Flag enabling cache

1 (default) | logical scalar

Flag enabling cache, specified as a logical scalar. When `EnableCache` is `True`, the `WebMapServer` object caches the `WMSCapabilites` object, which is returned when you use the `getCapabilities` method. The cache expires if the `AccessDate` property of the cached `WMSCapabilities` object is not the current day.

Data Types: `logical`

ServerURL — URL of the server

character vector

URL of the server, specified as a character vector. The URL must include the protocol `'http://'` or `'https://'`. The URL can contain additional WMS keywords.

Data Types: `char`

RequestURL — URL of the last request to the server

character vector

URL of the last request to the server, specified as a character vector. `RequestURL` specifies a request for either the XML capabilities document or a map. You can insert the requested URL into a browser.

Data Types: `char`

Object Functions

`getCapabilities` Get capabilities document from server

`getMap` Get raster map from server

`updateLayers` Update layer properties

Examples

Construct WebMapServer Object and Obtain Server Capabilities Document

Construct a `WebMapServer` object that communicates with one of the Environmental Research Division's Data Access Program (ERDDAP) WMS servers hosted by NOAA and obtains its capabilities document. Search for a server that provides daily, global sea

surface temperature (sst) data produced by the Jet Propulsion Laboratory's Regional Ocean Modeling System (JPL ROMS) group.

```
layers = wmsfind('coastwatch*jpl*sst', 'SearchField', 'serverurl');
serverURL = layers(1).ServerURL;
server = WebMapServer(serverURL);
capabilities = getCapabilities(server);
layers = capabilities.Layer;
```


Obtain data from the server. Show the boundaries of the nations and the global SST data.

```
nations = refine(layers, 'nations');
nations = nations(1);
sst = refine(layers, 'sst');
sst = sst(1);
layer = [sst nations];
request = WMSMapRequest(layer, server);
A = getMap(server, request.RequestURL);
R = request.RasterReference;
```

Display data from the server.

```
figure
worldmap(A,R)
geoshow(A,R)
title({sst.LayerTitle, sst.Details.Dimension.Default})
```

**GHRSSST Global 1-km Sea Surface Temperature (G1SST), Global, 0.01 Degree, Daily - SST
2015-06-15T00:00:00Z**



See Also

Functions

[wmsfind](#) | [wmsinfo](#) | [wmsread](#) | [wmsupdate](#)

Objects

[WMSCapabilities](#) | [WMSLayer](#) | [WMSMapRequest](#)

Introduced before R2006a

westof

Wrap longitudes to values west of specified meridian

Note The `westof` function is obsolete and will be removed in a future release of the toolbox. Replace it with the following calls, which are also more efficient:

```
westof(lon,meridian,'degrees') ==> meridian-mod(meridian-lon,360)
```

```
westof(lon,meridian,'radians') ==> meridian-mod(meridian-lon,2*pi)
```

Syntax

```
lonWrapped = westof(lon,meridian)
lonWrapped = westof(lon,meridian,angleunits)
```

Description

`lonWrapped = westof(lon,meridian)` wraps angles in `lon` to values in the interval `(meridian-360 meridian]`. `lon` is a scalar longitude or vector of longitude values. All inputs and outputs are in degrees.

`lonWrapped = westof(lon,meridian,angleunits)` where `angleunits` specifies the input and output units as either `'degrees'` or `'radians'`. It may be abbreviated and is case-insensitive. If *angleunits* is `'radians'`, the input is wrapped to the interval `(meridian-2*pi meridian]`.

Introduced before R2006a

wgs84Ellipsoid

Reference ellipsoid for World Geodetic System 1984

Syntax

```
E = wgs84Ellipsoid
E = wgs84Ellipsoid(lengthUnit)
```

Description

`E = wgs84Ellipsoid` returns a `referenceEllipsoid` object representing the World Geodetic System of 1984 (WGS 84) reference ellipsoid. The semimajor axis and semiminor axis are expressed in meters.

`E = wgs84Ellipsoid(lengthUnit)` returns a WGS 84 reference ellipsoid object in which the semimajor axis and semiminor axis are expressed in the specified unit, `lengthUnit`.

Input Arguments

lengthUnit — Unit of measure

'meter' (default) | string scalar | character vector

Unit of measure, specified as a string scalar or character vector. You can specify any length unit accepted by the `validateLengthUnit` function.

Data Types: char | string

Output Arguments

E — WGS84 reference ellipsoid

`referenceEllipsoid` object

WGS84 reference ellipsoid, returned as a `referenceEllipsoid` object.

Examples

Create wgs84 Reference Ellipsoid and View Derived Property

Create a World Geodetic System of 1984 (wgs84) reference ellipsoid and view one of its derived properties.

```
wgs84InMeters = wgs84Ellipsoid
```

```
wgs84InMeters =
```

```
referenceEllipsoid with defining properties:
```

```

        Code: 7030
        Name: 'World Geodetic System 1984'
        LengthUnit: 'meter'
        SemimajorAxis: 6378137
        SemiminorAxis: 6356752.31424518
        InverseFlattening: 298.257223563
        Eccentricity: 0.0818191908426215
```

```
and additional properties:
```

```

        Flattening
        ThirdFlattening
        MeanRadius
        SurfaceArea
        Volume
```

View value of SurfaceArea property.

```
wgs84InMeters.SurfaceArea
```

```
ans =
```

```
5.1007e+14
```

Create wgs84 Reference Ellipsoid Specifying Units

Create a World Geodetic System of 1984 (wgs84) reference ellipsoid, specifying the unit of measure. In the summary information returned, note the value of the LengthUnit field.

```
wgs84InKilometers = wgs84Ellipsoid('km')
```

```
wgs84InKilometers =
```

```
referenceEllipsoid with defining properties:
```

```
    Code: 7030
    Name: 'World Geodetic System 1984'
    LengthUnit: 'kilometer'
    SemimajorAxis: 6378.137
    SemiminorAxis: 6356.75231424518
    InverseFlattening: 298.257223563
    Eccentricity: 0.0818191908426215
```

```
and additional properties:
```

```
    Flattening
    ThirdFlattening
    MeanRadius
    SurfaceArea
    Volume
```

See Also

[referenceEllipsoid](#) | [validateLengthUnit](#)

Introduced in R2012a

wmclose

Close web map

Syntax

```
wmclose  
wmclose(wm)  
wmclose all
```

Description

wmclose closes the current web map.

wmclose(wm) closes the web map specified by wm.

wmclose all closes all web maps.

Examples

Close Current Web Map

Open a web map, pause one second, and then close the web map.

```
webmap  
pause(1)  
wmclose
```

Close Specified Web Map

Open two web maps, pause for one second, and then close one of the web maps.

```
h1 = webmap;  
h2 = webmap('ocean basemap');
```

```
pause(1)
wmclose(h1)
```

Close All Web Maps

Open two web maps, pause for one second, and then close all the web maps.

```
h1 = webmap;
h2 = webmap('ocean basemap');
pause(1)
wmclose all
```

Input Arguments

wm — Web map

web map handle

Web map, specified as a web map handle. You use the `webmap` function to get a web map handle when you create a web map.

See Also

`webmap` | `wmcenter` | `wmlimits` | `wmline` | `wmmarker` | `wmprint` | `wmremove` | `wmzoom`

Introduced in R2013b

wmprint

Print web map

Syntax

```
wmprint()  
wmprint(wm)
```

Description

`wmprint()` prints the contents of the current web map to a printer.

`wmprint(wm)` prints the contents of the web map specified by `wm`.

Examples

Print Web Map

Create a web map, specifying a base layer.

```
webmap('OpenStreetMap')
```

Position the web map.

```
wmcenter(51.487, 0, 15)
```

Print the contents of the web map.

```
wmprint()
```

Input Arguments

wm — Web map

scalar web map handle

Web map, specified as a scalar web map handle.

See Also

webmap | wmceneter | wmclose | wmlimits | wmline | wmmarker | wmremove | wmzoom

Introduced in R2013b

wmmarker

Display geographic marker on web map

Syntax

```
wmmarker(lat, lon)
wmmarker(P)
wmmarker(wm, ___)
wmmarker(__, Name, Value)
h = wmmarker( ___ )
```

Description

`wmmarker(lat, lon)` displays a marker overlay at the points specified by `lat` and `lon` on the current web map. If there is no current web map, `wmmarker` creates one.

`wmmarker` centers the map so that all vector overlays on the web map are visible. A marker is also called a map pin.

`wmmarker(P)` displays marker overlay specified by the latitude and longitude data in the geopoint vector `P`. Each element of `P` defines one marker overlay.

`wmmarker(wm, ___)` displays the overlay in the web map specified by the web map handle, `wm`.

`wmmarker(__, Name, Value)` specifies name-value pairs that set additional display properties. Parameter names can be abbreviated and are case-insensitive.

`h = wmmarker(___)` returns a handle to the overlay.


Examples

Draw Marker on Web Map

Add a marker positioned at London, England.

1 Functions — Alphabetical List

```
lat = 51.5187666404504;  
lon = -0.130003487285315;  
wmmarker(lat, lon);
```



wmmarker adds the marker to the list of overlays in the Layer Manager. In the illustration, note the default marker overlay name.

Marker listed as overlay.



Geographic Coordinates: 51.51822, -0.11080

- Base Layers
 - World Street Map
 - Open Street Map
 - World Imagery
 - World Topographic Map
 - World Shaded Relief
 - World Physical Map
 - World Terrain Base
 - USGS Imagery
 - USGS Topographic Imagery
 - USGS Shaded Topographic Map
 - USGS Shaded Relief
 - National Geographic Map
 - DeLorme World Basemap
 - Ocean Basemap
 - World Navigation Charts
 - Light Gray Canvas Map
- Overlay Layers
 - World Boundaries (Light Text)
 - World Boundaries (Dark Text)
 - World Reference
 - USA Weather NexRad Radar
 - Marker Overlay 1

Draw Markers at Features Defined in geopoint Vector

Read feature data into geopoint vector.

```
p = gpxread('boston_placenames');
```

Draw markers at features defined in the geopoint vector. `wmmarker` creates the web map. In the illustration, note the feature name in the balloon and the overlay name in the Layer Manager, which were specified in the call to `wmmarker`.

```
wmmarker(p, 'FeatureName', p.Name, 'OverlayName', 'Boston Placenames')
```


Web Browser - Web Map Display

Web Map Display

'BACK BAY'

| | |
|-------------|-------------|
| Name | 'BACK BAY' |
| Description | PPL-SUBDVSN |

500 m
2000 ft
Scale = 1 : 27K

Sources: Esri, HERE, DeLorme, USGS, Intermap, iPC, NRCAN, Esri Japan, METI, Esri China (Hong Kong), Esri (Thailand), MapmyIndia, TomTom, © OpenStreetMap, GIS User Comm.
Tiles Courtesy of [Esri ArcGIS Online](#)

Draw Marker Using Custom Icon and Description Data

Define location. For this example, the coordinates mark the location of The MathWorks, Inc.

```
lat = 42.299827;  
lon = -71.350273;
```

Specify text in description balloon and name. This code makes the MathWorks URL a link.

```
description = sprintf('%s<br>%s</br><br>%s</br>', ...  
                    '3 Apple Hill Drive', 'Natick, MA. 01760', ...  
                    '<a href="https://www.mathworks.com" target="_blank">https://www');  
name = 'The MathWorks, Inc.';
```

Specify custom icon.

```
iconDir = fullfile(matlabroot,'toolbox','matlab','icons');  
iconFilename = fullfile(iconDir, 'matlabicon.gif');
```

Draw marker on web map, specifying Description, FeatureName, Icon, and OverlayName. `wmmarker` creates the web map. In the illustration, note the custom icon and the HTML formatting in the description.

```
wmmarker(lat, lon, 'Description', description, ...  
         'FeatureName', name, ...  
         'Icon', iconFilename, ...  
         'OverlayName', name);
```


The screenshot shows a web browser window titled "Web Browser - Web Map Display". The address bar contains "Web Map Display". The map displays a street grid in Natick, MA, with a red line representing Route 9 (RT-9). A popup window is centered on the map, displaying the following information:

The MathWorks, Inc.
3 Apple Hill Drive
Natick, MA. 01760
<https://www.mathworks.com>

Map controls include a compass, a scale bar (100m / 500ft), and a scale of 1:6771. The bottom status bar reads "Waiting for web map page to load." and lists data sources: Esri, HERE, DeLorme, USGS, Intermap, iPC, NRCAN, Esri Japan, METI, Esri China (Hong Kong), Esri (Thailand), MapmyIndia, TomTom, © OpenStreetMap, GIS User Comm, and Tiles Courtesy of Esri ArcGIS Online.

Draw Marker Overlay Using Attribute Spec

Import a shapefile representing tsunami (tidal wave) events reported over several decades, tagged geographically by source location.

```
S = shaperead('tsunamis', 'UseGeoCoords', true);
```

Convert the geostruct returned by `shaperead` into a geopoint vector.

```
p = geopoint(S);
```


Create an attribute spec and modify it to define a table of values to display in the feature balloon, including year, cause, country, location, and maximum height. The attribute spec defines the format of the expected value for each field.

```
attribspec = makeattribspec(p);
```

```
desiredAttributes = ...  
    {'Max_Height', 'Cause', 'Year', 'Location', 'Country'};  
allAttributes = fieldnames(attribspec);  
attributes = setdiff(allAttributes, desiredAttributes);  
attribspec = rmfield(attribspec, attributes);  
attribspec.Max_Height.AttributeLabel = '<b>Maximum Height</b>';  
attribspec.Max_Height.Format = '%.1f Meters';  
attribspec.Cause.AttributeLabel = '<b>Cause</b>';  
attribspec.Year.AttributeLabel = '<b>Year</b>';  
attribspec.Year.Format = '%.0f';  
attribspec.Location.AttributeLabel = '<b>Location</b>';  
attribspec.Country.AttributeLabel = '<b>Country</b>';
```

Create a web map, specifying the base layer. Then add the marker overlay. In the illustration, note the table containing the data you specified in the attribute spec.

```
webmap('ocean basemap', 'WrapAround', false);  
wmmarker(p, 'Description', attribspec, ...  
    'OverlayName', 'Tsunami Events')  
wmzoom(2)
```



Input Arguments

lat — Latitudes of points
matrix

Latitudes of points, specified as a matrix.

Data Types: `single` | `double`

lon — Longitudes of points

matrix

Longitudes of points, specified as a matrix.

Data Types: `single` | `double`

P — Geographic features

geopoint vector

Geographic features, specified as a geopoint vector.

wm — Web map

web map handle

Web map, specified as a web map handle.

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

Example: `wmmarker(lat, lon, 'Autofit', true)`

Autofit — Overlay visibility

`true` (default) | `false`

Overlay visibility, specified as the comma-separated pair consisting of 'Autofit' and the logical flag `true` or `false`, or the numeric value 1 or 0. If `true` or 1, `wmmarker` adjusts the spatial extent of the map to ensure that all the vector overlays on the map are visible. If `false`, `wmmarker` does not adjust the spatial extent when the overlay is added to the map.

Overlay visibility, specified as a scalar logical or numeric value `true` (1) or `false` (0).

- If `true`, `wmmarker` adjusts the spatial extent of the map to ensure that all the vector overlays on the map are visible.

- If `false`, `wmmarker` does not adjust the spatial extent when the overlay is added to the map.

Data Types: `double` | `logical`

Description — Description of feature

empty character vector (' ') (default) | character vector | cell array of character vectors
| scalar structure

Description of feature, specified as the comma-separated pair consisting of 'Description' and a character vector, cell array of character vectors, or scalar structure. The description defines the content that `wmmarker` displays in the feature's description balloon which appears when a user clicks on the feature in the web map. Description elements can be either plain text or HTML markup. When you specify an attribute spec, the display in the balloon for the attribute fields of `P` are modified according to the specification. The default value is an empty character vector (' '). If the value is a structure, the attribute spec is applied to the attributes of each feature of `P` and ignored with `lat` and `lon` input.

- If the value is a cell array it is either scalar or the same length as `P`, or `lat` and `lon`, and specifies the description for each marker.
- If the value is a structure, the attribute spec is applied to the attributes of each feature of `P` and ignored with `lat` and `lon` input.

Data Types: `char` | `struct` | `cell`

OverlayName — Name of overlay layer

'Marker Overlay *N*', (default) | character vector

Name of overlay layer, specified as the comma-separated pair consisting of 'OverlayName' and a character vector. `wmmarker` inserts the name in the Layer Manager under the Overlays item. The Layer Manager is the tool that appears on the right side of the web map frame. The default name is 'Marker Overlay *N*' where *N* is the number assigned to this overlay.

Data Types: `char`

FeatureName — Name of feature

'*OverlayName*: Point *K*' (default) | character vector | cell array of character vectors

Name of feature, specified as the comma-separated pair consisting of 'FeatureName' and a character vector or cell array of character vectors. The name appears in the

feature's balloon when a user clicks on the feature in the web map. The default value is '*OverlayName* : Point *K*', where *OverlayName* is the name of the overlay and *K* is the number assigned to a particular point. If the value is a character vector, `wmmarker` applies it to all features. If the value is a cell array, it must be a scalar or an array with the same length as `P` or `lat` and `lon`.

Data Types: `char` | `cell`

Icon — File name of custom icon for a marker

character vector | cell array of character vectors

File name of custom icon for a marker, specified as the comma-separated pair consisting of '`Icon`' and a character vector or cell array of character vectors. If the icon filename is not in the current folder, or in a folder on the MATLAB path, specify a full or relative pathname. If you specify an Internet URL it must include the protocol type. If the icon filename is not specified, the default icon is displayed. For best results when you want to view a non-default icon, specify a PNG file containing image data with an alpha mask.

- If the value is a character vector, `wmmarker` applies the value to all markers.
- If you specify a cell array, it must be the same length as `P`, or `lat` and `lon`, and specifies the icon for each marker.

Data Types: `char` | `cell`

IconScale — Scaling factor for icon

1 (default) | positive numeric scalar or vector.

Scaling factor for icon, specified as the comma-separated pair consisting of '`IconScale`' and a positive numeric scalar or vector.

- If the value is a scalar, the value is applied to all icons.
- If the value is a vector, it must specify a value for each icon, and it must be the same length as `lat` and `lon` or `P`.

Data Types: `double`

Color — Color of icon

'red' (default) | `ColorSpec` | cell array of character vectors | *M*-by-3 numeric array

Color of icon, specified as the comma-separated pair consisting of '`Color`' and a MATLAB Color Specification (`ColorSpec`), a cell array of color names, or a numeric array. The color is applied to the icon when a custom icon file has not been specified,

otherwise it is ignored. The default value is 'red'. If the value is a cell array, it must be the same length as LAT and LON, or P. If the value is a numeric array, it must be 1-by-3 or M -by-3 where M is the length of lat and lon or P.

- If the value is a cell array, it must be scalar or the same length as P.
- If the value is a numeric array, it must be an M -by-3 where M is either 1 or the length of P.

Data Types: double | char | cell

Alpha — Transparency of marker

1 (default) | numeric scalar or vector

Transparency of marker, specified as the comma-separated pair consisting of 'Alpha' and a numeric scalar or vector. If you specify a vector, it must include a value for each marker, that is, the vector must be the same length as P. The default value, 1, means that the marker is fully opaque.

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64

Output Arguments

h — Marker overlay

handle to a marker overlay object

Marker overlay, returned as a handle to a marker overlay object.

See Also

webmap | wmceneter | wmclose | wmlimits | wmline | wmpolygon | wmprint |
wmremove | wmzoom

Introduced in R2013b

wmline

Display geographic line on web map

Syntax

```
wmline(lat,lon)
wmline(P)
wmline(wm, ___ )
wmline( ___,Name,Value)
h = wmline( ___ )
```

Description

`wmline(lat,lon)` displays a line overlay defined by the vertices in `lat,lon` on the current web map. If there is no current web map, `wmline` creates one. `wmline` centers the map so that all vector overlays displayed on the web map are visible.

`wmline(P)` displays a line overlay based on the content of the geopoint or geoshape vector `P`.

`wmline(wm, ___)` displays the line overlay on the web map specified by the web map handle, `wm`.

`wmline(___,Name,Value)` specifies name-value pairs that set additional display properties.

`h = wmline(___)` returns a handle to line overlay.

Examples


Draw Line on Web Map

Find the latitude and longitude for London and Paris.


```
cities = shaperead('worldcities.shp', 'UseGeoCoords', true, ...  
    'Selector', ...  
    {@(v)(ismember(v, {'London', 'Paris'})), 'Name'});  
lat = [cities.Lat];  
lon = [cities.Lon];
```

Draw line on web map from London to Paris.

```
wmline(lat, lon)
```



Draw Reduced Line on Web Map

Large data sets can sometimes be slow to display, making the web map browser appear to hang. To work around this issue, reduce the size of the data set using the `reduce` function before calling `wmLine`.

Load vector data.


```
load coastlines
```

Reduce the number of points in the latitude and longitude vectors using the `reducem` function.

```
[lat, lon] = reducem(coastlat, coastlon);
```


Create a web map that does not wrap because the data is of global extent.

```
webmap('ocean basemap', 'WrapAround', false)
```



Draw coast lines on web map. The figure shows the description balloon that appears when you click on the line. The code sets the FeatureName attribute to “coastline”.

```
wmline(lat, lon, 'LineWidth', 3, 'FeatureName', 'coastline')  
wmzoom(2)
```




Draw Circles on Web Map

Define the latitude and longitude of the feature. This example shows how to draw lines on a web map that display range data for an airport approach pattern.

```
lat0 = 51.50487;  
lon0 = .05235;
```

Create a web map, specifying a base layer.

```
webmap('OpenStreetMap')
```




Compute a small circle with a 1000 meter radius. Setting the az parameter to an empty matrix causes `scircle1` to compute a complete circle.

```
radius = 1000;  
az = [];  
e = wgs84Ellipsoid;  
[lat, lon] = scircle1(lat0, lon0, radius, az, e);
```


Draw a red circle with 1000 meter radius, using the latitude and longitude values returned by `scircle1` in the previous step.

```
wmline(lat, lon, 'Color', 'red', 'OverlayName', '1000 Meters');
```




Compute another small circle, this time with a 2000 meter radius.

```
radius = 2000;  
[lat, lon] = scircle1(lat0, lon0, radius, az, e);
```

Draw the 2000 meter radius circle on the web map, setting the color to black.

```
wmline(lat, lon, 'Color', 'k', 'OverlayName', '2000 Meters');
```

Input Arguments

lat — Latitudes of vertices
 matrix

Latitudes of vertices, specified as a matrix.

Data Types: `single` | `double`

lon — Longitudes of vertices

matrix

Longitudes of vertices, specified as a matrix.

Data Types: `single` | `double`

P — Geographic features

geopoint vector | geoshape vector

Geographic features, specified as a geopoint or geoshape vector.

- If **P** is a geopoint vector, the overlay contains a single line connecting its vertices.
- If **P** is a geoshape vector, the overlay contains one line feature for each element of **P**.

wm — Web map

web map handle

Web map, specified as a web map handle.

Name-Value Pair Arguments

Specify optional comma-separated pairs of **Name**, **Value** arguments. **Name** is the argument name and **Value** is the corresponding value. **Name** must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as **Name1**, **Value1**, . . . , **NameN**, **ValueN**.

Example: `wmline(lat,lon,'OverlayName','Shortest Route');`

Autofit — Overlay visibility

`true` (default) | `false`

Overlay visibility, specified as the comma-separated pair consisting of 'Autofit' and the scalar logical or numeric value `true` (1) or `false` (0).

- If `true`, `wmline` adjusts the spatial extent of the map to ensure that all the vector overlays on the map are visible.
- If `false`, `wmline` does not adjust the spatial extent when this vector layer is added to the map.

Data Types: double | logical

Description — Description of feature

empty character vector (' ') (default) | character vector | cell array of character vectors | scalar structure

Description of feature, specified as the comma-separated pair consisting of 'Description' and a character vector, cell array of character vectors, or a scalar structure. The description defines the content of the description balloon displayed when you click the feature in a web map. Description elements can be either plain text or HTML markup. When an attribute spec is provided, the display in the balloon for the attribute fields of P are modified according to the specification.

- If you specify a scalar cell array, wmline applies the value to all line features.
- If you specify a nonscalar cell array, the cell array must contain a value for each feature, that is, the cell array must be the same length as P.
- If the value is a structure, wmline applies the attribute specification to each line.

Data Types: char | struct | cell

OverlayName — Name of overlay layer

'Line Overlay N', (default) | character vector

Name of overlay layer, specified as the comma-separated pair consisting of 'OverlayName' and a character vector. wmline inserts the name in the Layer Manager under the "Overlays" item. The Layer Manager is the tool that appears on the right side of the web map browser. The default name is 'Line Overlay N' where N is the number assigned to this overlay.

Data Types: char

FeatureName — Name of feature

'OverlayName: Line K' (default) | character vector | cell array of character vectors

Name of feature, specified as the comma-separated pair consisting of 'FeatureName' and character vector or cell array of character vectors. The name appears in the balloon that displays when you click the feature in the web map. The default value is 'OverlayName : Line K', where *OverlayName* is the name of the overlay and *K* is the number assigned to the particular line.

- If the value is a character vector, it applies to all features.

- If the value is a cell array of character vectors, it must be either a scalar or the same length as *P*.

Data Types: `char` | `cell`

Color — Line color

'black' (default) | `ColorSpec` | cell array of character vectors | *M*-by-3 double array

Line color, specified as the comma-separated pair consisting of 'Color' and a MATLAB Color Specification (`ColorSpec`), a cell array of color names, or a numeric array.

- If you specify a scalar cell array, `wmline` applies the value to all line features.
- If you specify a nonscalar cell array, the cell array must contain a value for each line feature, that is, the cell array must be the same length as *P*.
- If the value is a numeric array, it must be *M*-by-3, where *M* is either 1 or the length of *P*.

Data Types: `double` | `char` | `cell`

LineWidth — Width of line in pixels

1 (default) | positive numeric scalar or vector

Width of line in pixels, specified as the comma-separated pair consisting of `LineWidth` and a positive numeric scalar or vector. If you specify a vector, it must include a value for each line, that is, the vector must be the same length as *P*.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64`

Alpha — Transparency of line

1 (default) | numeric scalar or vector

Transparency of line, specified as the comma-separated pair consisting of 'Alpha' and a numeric scalar or vector. If you specify a vector, it must include a value for each line, that is, the vector must be the same length as *P*. The default value, 1, means that the line is fully opaque.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64`

Output Arguments

h — Overlay layer

handle to line overlay

Overlay layer, returned as a handle to a line overlay.

Tips

- Under certain conditions, when you zoom in on a line overlay in a web map, parts of the line may become invisible. This can occur if the data is one long line segment that is composed of many parts. To workaroud this issue, break the long line into a series of line segments by inserting NaNs in the line data.

See Also

[webmap](#) | [wmcenter](#) | [wmclose](#) | [wmlimits](#) | [wmmarker](#) | [wmpolygon](#) | [wmprint](#) | [wmremove](#) | [wmzoom](#)

Introduced in R2013b

wmpolygon

Display geographic polygon on web map

Syntax

```
wmpolygon(lat,lon)
wmpolygon(P)
wmpolygon(wm, ___ )
wmpolygon( ___ ,Name,Value)
h = wmpolygon( ___ )
```

Description

`wmpolygon(lat,lon)` displays the polygon overlay defined by the vertices in `lat` and `lon` on the current web map. If there is no current web map, `wmpolygon` creates one. `wmpolygon` centers and scales the map so that all the vector overlays displayed in the web map are visible.

`wmpolygon(P)` displays a polygon overlay based on the content of the polygon geoshape vector `P`. The overlay contains one polygon feature for each element of `P`.

`wmpolygon(wm, ___)` displays the overlay in the web map specified by the web map handle, `wm`.

`wmpolygon(___ ,Name,Value)` specifies name-value pairs that set additional display properties.

`h = wmpolygon(___)` returns a handle to the overlay.

Examples


Display Coastlines as a Polygon

Load coastline data from a MAT-file.

```
load coastlines
```

Display the coast lines as a polygon overlay layer.

```
wmpolygon(coastlat,coastlon,'OverlayName','Polygon coastlines')
```



Display Polygon with Inner Ring


Define coordinates of rings. For this example, the coordinates define a location centered on the Eiffel Tower.

```
lat0 = 48.858288;  
lon0 = 2.294548;  
outerRadius = .01;  
innerRadius = .005;  
[lat1,lon1] = scircle1(lat0,lon0,outerRadius);  
[lat2,lon2] = scircle1(lat0,lon0,innerRadius);  
lat2 = flipud(lat2);  
lon2 = flipud(lon2);  
lat = [lat1; NaN; lat2];  
lon = [lon1; NaN; lon2];
```

Display on web map.

```
webmap('worldimagery')  
wmpolygon(lat,lon,'EdgeColor','g','FaceColor','c','FaceAlpha',.5)
```

1 Functions — Alphabetical List



Display USA State Boundaries Using Political Colormap

Read state boundary data from shapefile in polygon geoshape.

```
p = shaperead('usastatelo.shp','UseGeoCoords',true);  
p = geoshape(p);
```

Define the colors you want to use for the polygons.

```
colors = polcmap(length(p));
```

Display the polygons as an overlay on a web map. The example uses the FaceAlpha parameter to make the polygons semi-transparent.

```
webmap('worldphysicalmap')  
wmpolygon(p,'FaceColor',colors,'FaceAlpha',.5,'EdgeColor','k', ...  
          'EdgeAlpha',.5,'OverlayName','USA Boundary','FeatureName',p.Name)
```


Display Reduced High Resolution Polygon Data on Web Map

Large data sets can sometimes be slow to display, making the web map browser appear to hang. This example shows how to reduce the size of a data set using `reducem` before calling `wmpolygon`.

- 1 Load high-resolution vector data into the workspace.


```
states = shaperead('usastatehi.shp','UseGeoCoords', true);
states = geoshape(states);
```

- 2 Reduce the number of points in the latitude and longitude vectors using the `reducem` function.

```
for k = 1:length(states)
    [states(k).Latitude, states(k).Longitude] = reducem( ...
        states(k).Latitude', states(k).Longitude');
end
```

- 3 Display state boundaries on the web map. Note that the borders of the reduced polygons may not meet if you zoom in on them.

```
colors = polcmap(length(states));
webmap('worldphysicalmap')
wmpolygon(states,'FaceColor',colors,'FaceAlpha',.5,'EdgeColor','k', ...
    'EdgeAlpha',.5,'OverlayName','USA Boundary','FeatureName',states.Name)
```



Input Arguments

lat — Latitude vertices

matrix in the range [-90, 90]

Latitude vertices, specified as matrix in the range [-90, 90].

Data Types: `single` | `double`

lon — Longitude vertices

matrix

Longitude of vertices, specified as a matrix.

Data Types: `single` | `double`

P — Geographic features

polygon geoshape vector

Geographic features, specified as a polygon geoshape vector.

wm — Web map

handle to a web map

Web map, specified as a handle to a web map.

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

Example: `wmpolygon(lat, lon, 'Autofit', true)`

Autofit — Overlay visibility

`true` (default) | `false`

Overlay visibility, specified as the comma-separated pair consisting of 'Autofit' and the scalar logical or numeric value `true` (1) or `false` (0).

- If `true`, `wmpolygon` adjusts the spatial extent of the map to ensure that all the vector overlays on the map are visible.

- If `false`, `wmpolygon` does not adjust the spatial extent of the map when this vector layer is added to the map.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64` | `logical`

Description — Description of feature

empty character vector (default) | character vector | cell array of character vectors | scalar structure

Description of feature, specified as the comma-separated pair consisting of 'Description' and a character vector, cell array of character vectors, or a scalar structure.

- If you specify a character vector, the text defines the content displayed in the description balloon, which appears when you click the feature in the web map. Description elements can be either plain text or marked up with HTML markup.
- If you specify a cell array, it must be either a scalar or the same length as `P`, and specifies the description for each polygon.
- If the value is a structure (attribute specification), `wmpolygon` displays the attribute fields of `P` in the balloon, modified according to the specification.

Data Types: `char` | `struct` | `cell`

OverlayName — Name of overlay layer

'Polygon Overlay *N*', (default) | character vector

Name of overlay layer, specified as the comma-separated pair consisting of 'OverlayName' and a character vector. `wmpolygon` inserts the name in the Layer Manager under the "Overlays" item. The Layer Manager is the tool that appears on the right side of the web map browser. The default name is 'Polygon Overlay *N*' where *N* is the number assigned to this overlay.

Data Types: `char`

FeatureName — Name of feature

'OverlayName: Line *K*' (default) | character vector | cell array of character vectors

Name of feature, specified as the comma-separated pair consisting of 'FeatureName' and character vector or cell array of character vectors. The name appears in the balloon when you click the feature in the web map. The default value is 'OverlayName:

Polygon K' , where *OverlayName* is the name of the overlay and K is the number assigned to the particular polygon.

- If the value is a character vector, it applies to all features.
- If the value is a cell array of character vectors, it must be either a scalar or the same length as P .

Data Types: char | cell

FaceColor — Color of polygon faces

'black' (default) | ColorSpec | cell array of character vectors | m -by-3 double array | 'none'

Color of polygon faces, specified as the comma-separated pair consisting of 'FaceColor' and a MATLAB Color Specification (ColorSpec), a cell array of color names, or a numeric array. The value 'none' indicates that the polygons are not filled.

- If the value is a cell array, it must be scalar or the same length as P .
- If the value is a numeric array, it must be an m -by-3 where m is either 1 or the length of P .

Data Types: double | char | cell

FaceAlpha — Transparency of polygon faces

1 (default) | numeric scalar or vector in the range [0, 1]

Transparency of polygon faces, specified as the comma-separated pair consisting of 'FaceAlpha' and a numeric scalar or vector in the range [0, 1]. The default value, 1, means that the polygon is fully opaque.

- If the value is a scalar, it applies to all polygon faces.
- If the value is a vector, it must be the same length as P .

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64

EdgeColor — Color of polygon edges

'none' (default) | ColorSpec | cell array of character vectors | m -by-3 double array

Color of polygon edges, specified as the comma-separated pair consisting of 'EdgeColor' and a MATLAB Color Specification (ColorSpec), a cell array of color names, or a numeric array. The value 'none' indicates that the polygons have no edges.

- If the value is a cell array, it must be scalar or the same length as P.
- If the value is a numeric array, it must be m -by-3, where m is either 1 or the length of P.

Data Types: double | char | cell

EdgeAlpha — Transparency of polygon edges

1 (default) | numeric scalar or vector in the range [0, 1]

Transparency of polygon edges, specified the comma-separated pair consisting of 'EdgeAlpha' and as a numeric scalar or vector in the range [0, 1].

- If the value is a scalar, it applies to all polygon faces.
- If the value is a vector, it must be the same length as P.

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64

LineWidth — Width of polygon edges

1 (default) | positive numeric scalar or vector

Width of polygon edges, specified as the comma-separated pair consisting of 'LineWidth' and a positive numeric scalar or vector.

- If the value is a scalar, it applies to all polygon faces.
- If the value is a vector, it must be the same length as P.

Example:

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64

Output Arguments

h — Polygon overlay

handle to polygon overlay

Polygon overlay, returned as a handle to the polygon overlay.

Tips

- When you move the cursor over the polygons you define on an image and click, `wmpolygon` displays a description balloon and disables panning. If you move the cursor off the polygon, you can still click and pan the image. You can also use the arrow keys to pan the image.

See Also

Functions

`webmap` | `wmcenter` | `wmclose` | `wmlimits` | `wmline` | `wmmarker` | `wmprint` | `wmremove` | `wmzoom`

Objects

`geoshape`

Introduced in R2016a

wmremove

Remove overlay on web map

Syntax

```
wmremove()  
wmremove(h)
```

Description

`wmremove()` removes the overlay most recently inserted into the current web map.

`wmremove(h)` removes the overlay or overlays specified by the scalar overlay handle or vector of overlay handles.

Examples

Remove a Marker Overlay

Draw a marker on a web map. `wmmarker` creates the web map. Pause, and then remove the marker overlay.

```
wmmarker(42, -73);  
pause(1);  
wmremove()
```

Remove Multiple Overlays

Draw several marker overlays on a web map. `wmmarker` creates the web map. Pause, and then remove the marker overlays, specifying a vector of overlay handles.

```
h1 = wmmarker(42, -80);  
h2 = wmmarker(42, -78);
```

```
pause(1);  
wmremove([h1 h2])
```

Remove Line Overlay

Create a web map.

```
wm = webmap();
```

Load coastline data and display it as an overlay on the webmap.

```
load coastlines  
h = wmline(coastlat, coastlon);
```

Remove the overlay specified by h.

```
wmremove(h)
```

Input Arguments

h — Web map overlay

scale overlay handle or vector of overlay handles

Web map overlay, specified as a scalar overlay handle or a vector of overlay handles.

See Also

webmap | wmcenter | wmclose | wmlimits | wmline | wmmarker | wmprint | wmzoom

Introduced in R2013b

wmcenter

Set or obtain web map center point

Syntax

```
wmcenter(centerLatitude,centerLongitude)
wmcenter(wm,centerLatitude,centerLongitude)
wmcenter( ____,zoomLevel)
[lat,lon] = wmcenter()
[lat,lon] = wmcenter(wm)
```

Description

`wmcenter(centerLatitude,centerLongitude)` centers the current web map at the specified latitude and longitude. If there is no current web map, `wmcenter` creates a new web map.

`wmcenter(wm,centerLatitude,centerLongitude)` centers the web map, specified by the handle `wm`, at the specified latitude and longitude.

`wmcenter(____,zoomLevel)` centers and zooms the web map to the specified zoom level.

`[lat,lon] = wmcenter()` returns the latitude and longitude of the center point of the current web map.

`[lat,lon] = wmcenter(wm)` returns the latitude and longitude of the center point of the web map specified by the handle `wm`.

Examples

Display web map and center it

Display a map a find it's center point. `wmcenter` creates a web map if none exists.


```
[centerLatitude, centerLongitude] = wmcenter()
```

```
centerLatitude =
```

```
    0
```


```
centerLongitude =
```

```
    0
```



Center the map at the specified center point.


```
wmcenter(51.52, 0)
```

Display Multiple Web Maps Centered and Zoomed


Create two web maps.

```
wm1 = webmap;  
wm2 = webmap('USGSImagery');
```




Click the tile vertically button so that both maps are visible at the same time.

Click to tile maps side-by-side.



Center the two web maps, specifying the zoom level as well.

```
centerLatitude = 36.1;
centerLongitude = -113.2;
zoomLevel = 10;
wmcenter(wm1, centerLatitude, centerLongitude, zoomLevel)
wmcenter(wm2, centerLatitude, centerLongitude, zoomLevel)
```

Input Arguments

centerLatitude — Latitude of center point

scalar in the range $[-90\ 90]$ of type `single` or `double`

Latitude of center point, specified as a scalar in the range $[-90\ 90]$ of type `single` or `double`.

Data Types: `single` | `double`

centerLongitude — Longitude of center point

scalar in the range $[-180\ 180]$ of type `single` or `double`

Longitude of center point, specified as a scalar in the range [-180 180] of type single or double.

Data Types: single | double

wm — Web map

web map handle

Web map, specified as a web map handle.

zoomLevel — Zoom level

scalar numeric integer in the range [0 18] of type single or double

Zoom level, specified as a scalar numeric integer in the range [0 18] of type single or double.

Data Types: single | double

Output Arguments

lat — Latitude of center point

scalar in the range [-90 90] of type single or double

Latitude of center point, returned as a scalar in the range [-90 90] of type single or double.

Data Types: single | double

lon — Longitude of center point

scalar in the range [-180 180] of type single or double

Longitude of center point, returned as a scalar in the range [-180 180] of type single or double.

Data Types: single | double

Tips

- Particular maps may not support every available zoom level. If your map displays as completely white, try another zoom level. The map you are displaying may not support

the zoom level you have currently selected. You can also select another base layer, which might support the specified zoom level.

See Also

`webmap` | `wmclose` | `wmlimits` | `wmline` | `wmmarker` | `wmprint` | `wmremove` | `wmzoom`

Introduced in R2013b

wmzoom

Set or obtain zoom level of web map

Syntax

```
wmzoom(zoomLevel)
wmzoom(wm, zoomLevel)
zoomLevelOut = wmzoom()
zoomLevelOut = wmzoom(wm)
```

Description

`wmzoom(zoomLevel)` specifies the zoom level of the current web map, `zoomLevel`. If there is no current web map, `wmzoom` creates a new web map.

`wmzoom(wm, zoomLevel)` specifies the zoom level of the web map, specified by the handle `wm`.

`zoomLevelOut = wmzoom()` returns the zoom level of the current web map.

`zoomLevelOut = wmzoom(wm)` returns the zoom level of the web map specified by the handle `wm`.

Examples

Get Zoom Level of Current Web Map and Specify New Zoom Level

Create a web map at default zoom level.

```
zoomLevel = wmzoom()
```

```
zoomLevel =
```

```
0
```

Zoom in and center the web map at the specified latitude and longitude (London).

```
wmzoom(10)
wmcenter(51.52, 0)
```

Specify Zoom Level of Several Web Maps

Create two web maps.

```
wm1 = webmap;
wm2 = webmap('worldtopographic');
```

Zoom in and center both maps at a specified latitude and longitude (Paris).

```
lat = 48.821;
lon = 1.9391;
zoomLevel = 10;
```

```
wmzoom(wm1, zoomLevel)
wmcenter(wm1, lat, lon)
wmzoom(wm2, zoomLevel)
wmcenter(wm2, lat, lon)
```

Input Arguments

zoomLevel — Zoom level

scalar numeric integer in the range [0 18]

Zoom level, specified as a scalar numeric integer in the range [0 18].

Data Types: `single` | `double`

wm — Web map

web map handle

Web map, specified as a web map handle.

Output Arguments

zoomLevelOut — Zoom level of the current web map

scalar numeric integer in the range [0 18]

Zoom level of the current web map, returned as a scalar numeric integer in the range [0 18].

Data Types: `single` | `double`

Tips

- Particular maps may not support every available zoom level. If your map displays as completely white, try another zoom level. The map you are displaying may not support the zoom level you have currently selected. You can also select another base layer, which might support the specified zoom level.

See Also

`webmap` | `wmcenter` | `wmclose` | `wmlimits` | `wmline` | `wmmarker` | `wmprint` | `wmremove`

Introduced in R2013b

wmlimits

Set or obtain web map limits

Syntax

```
wmlimits(latitudeLimits, longitudeLimits)
wmlimits(wm, latitudeLimits, longitudeLimits)
[latlim, lonlim] = wmlimits()
[latlim, lonlim] = wmlimits(wm)
```

Description

`wmlimits(latitudeLimits, longitudeLimits)` center the current web map within the specified latitude limits and the longitude limits. If there is no current web map, `wmlimits` creates one.

Note The resulting limits often do not match the specified limits because the zoom level is quantized to discrete integer values and the longitude limits may be constrained if the map was constructed with the `WrapAround` property equal to `false`.

`wmlimits(wm, latitudeLimits, longitudeLimits)` centers the web map specified by the web map handle `wm` within the specified latitude limits and longitude limits.

`[latlim, lonlim] = wmlimits()` returns the latitude and longitude limits of the current web map.


`[latlim, lonlim] = wmlimits(wm)` returns the latitude and longitude limits of the web map specified by `wm`.

Examples

Display Web Map Centered Within Specified Limits

Specify latitude and longitude limits. `wmlimits` creates the web map.

```
wmlimits([37, 42], [-108.9, -100.7])
```



Get the latitude and longitude limits of the current web map. (Note: The limits returned depend on the size of the web map frame and the zoom level. Your results may differ from the results shown in this example.)


```
[latitudeLimits, longitudeLimits] = wmlimits()
latitudeLimits =
    34.8664    43.9282

longitudeLimits =
   -112.9519   -96.6481
```

Display Several Web Maps Centered Within Specified Limits

Create two web maps, specifying different base layers.


```
wm1 = webmap;
wm2 = webmap('worldtopographic');
```



Click the tile vertically button to make both makes visible at the same time.


1 Functions — Alphabetical List

Click to tile maps side-by-side.



Specify latitude and longitude limits and apply to both maps to get two different views of the same region.

```
latitudeLimits = [37, 42];  
longitudeLimits = [-108.9, -100.7];  
wmlimits(wm1, latitudeLimits, longitudeLimits)  
wmlimits(wm2, latitudeLimits, longitudeLimits)
```



Input Arguments

latitudeLimits – Latitude limits in degrees

1-by-2 row vector of type double

Latitude limits in degrees, specified as a 1-by-2 row vector of type double of the form [southern-limit northern-limit].

Example: [37, 42]

Data Types: double

longitudeLimits — Longitude limits in degrees

1-by-2 row vector of type `double`

Longitude limits in degrees, specified as a 1-by-2 row vector of type `double` of the form `[western-limit eastern-limit]`.

Example: `[-108.9, -100.7]`

Data Types: `double`

wm — Web map

scalar web map handle

Web map, specified as a scalar web map handle.

Output Arguments

latLim — Latitude limits in degrees

1-by-2 row vector of type `double`

Latitude limits in degrees, returned as a 1-by-2 row vector of type `double`.

Example: `[37, 42]`

Data Types: `double`

lonLim — Longitude limits in degrees

1-by-2 row vector of type `double`

Longitude limits in degrees, returned as a 1-by-2 row vector of type `double`.

Example: `[-108.9, -100.7]`

Data Types: `double`

See Also

`webmap` | `wmcenter` | `wmclose` | `wmline` | `wmmarker` | `wmprint` | `wmremove` | `wmzoom`

Introduced in R2013b

WMSCapabilities

Web Map Service capabilities document

Description

A `WMSCapabilities` object represents a Web Map Service (WMS) capabilities document obtained from a WMS server. A capabilities document is an XML document that contains metadata describing the geographic content offered by the server.

Creation

You can create a `WMSCapabilities` object using the `WMSCapabilities` function described here, or using the `wmsinfo` function to specify a timeout. A `WMSCapabilities` is also returned from the `getCapabilities` function when you have a `WebMapServer` object.

```
capabilities = WMSCapabilities(serverURL, capabilitiesResponse)
```

Description

`capabilities = WMSCapabilities(serverURL, capabilitiesResponse)` creates a `WMSCapabilities` object, setting the `ServerURL` property and defining the capabilities of the server using the XML elements in `capabilitiesResponse`.

Input Arguments

capabilitiesResponse — XML elements that describe the capabilities of the WMS server

character vector

XML elements that describe the capabilities of the WMS server, specified as a character vector.

Example: `'uint8=>char'`

Data Types: `char`

Properties

ServerTitle — Title of WMS server

character vector

Title of WMS server, specified as a character vector.

Data Types: char

ServerURL — URL of WMS server

character vector

URL of WMS server, specified as a character vector. The server URL must include the protocol 'http://' or 'https://'.

Data Types: char

ServiceName — Name of Web map service

character vector

Name of Web map service, specified as a character vector.

Data Types: char

Version — WMS version specification

character vector

WMS version specification, specified as a character vector.

Data Types: char

Abstract — Information about server

character vector

Information about server, specified as a character vector.

Data Types: char

OnlineResource — Online information about server

character vector

Online information about server, specified as a character vector.

Data Types: char

ContactInformation – Contact information for an individual or an organization structure

Contact information for an individual or an organization, specified as a **ContactInformation** structure, containing the following fields:

| Field Name | Data Type | Field Content |
|--------------|------------------|----------------------|
| Person | Character vector | Name of individual |
| Organization | Character vector | Name of organization |
| Email | Character vector | Email address |

Data Types: struct

AccessConstraints – Constraints inherent in accessing the server character vector

Constraints inherent in accessing the server, such as server load limits, specified as a character vector.

Data Types: char

Fees – Types of fees associated with accessing server character vector

Types of fees associated with accessing server, specified as a character vector.

Data Types: char

KeywordList – Descriptive keywords of the server character vector

Descriptive keywords of the server, specified as a character vector.

Data Types: char

ImageFormats – Image formats supported by server character vector

Image formats supported by server, specified as a character vector.

Data Types: char

LayerNames — Layer names provided by server

cell array of character vectors

Layer names provided by server, specified as a cell array of character vectors.

Data Types: cell

Layer — Information about layers on WMS server

WMSLayer array

Information about layers on WMS server, specified as an array of WMSLayer objects.

AccessDate — Date of request to server

character vector

Date of request to server, specified as a character vector.

Data Types: char

Object Functions

disp Display properties of WMS layers or capabilities

Examples

Create WMSCapabilities Object

Create a WMSCapabilities object from the contents of a downloaded capabilities file from the NASA SVS Image Server.

```
nasa = wmsfind('NASA SVS Image', 'SearchField', 'servertitle');
serverURL = nasa(1).ServerURL;
server = WebMapServer(serverURL);
capabilities = server.getCapabilities;
filename = 'capabilities.xml';
websave(filename, server.RequestURL);
```

```
fid = fopen(filename, 'r');
capabilitiesResponse = fread(fid, 'uint8=>char');
```

```
fclose(fid);  
capabilities = WMSCapabilities(serverURL, capabilitiesResponse);
```

- “Explore Other Layers using a Capabilities Document”

See Also

WMSLayer | WebMapServer | webservice | wmsinfo

Topics

“Explore Other Layers using a Capabilities Document”

Introduced in R2009b

wmsfind

Search local database for Web map servers and layers

Syntax

```
layers = wmsfind(querystr)
layers = wmsfind(querystr,Name,Value)
```

Description

`layers = wmsfind(querystr)` searches the fields of the installed Web Map Service (WMS) database for partial matches of *querystr*, which is a character vector, cell array of character vectors, string, or array of strings. By default, `wmsfind` searches the `Layer` or `LayerName` properties but you can include other fields in the search using the `SearchFields` parameter. *querystr* can contain the wildcard character '*'.

The WMS database contains the following searchable fields:

| Field | Data Type | Content |
|-------------|----------------------------|--|
| LayerTitle | character vector | Title of layer |
| LayerName | character vector | Name of layer |
| ServerTitle | character vector | Title of server |
| ServerURL | character vector | URL of server |
| Latlim | two-element numeric vector | latitude limits of the layer in the form [southern northern] |
| Lonlim | two-element numeric vector | longitude limits of the layer in the form [western eastern] |

By default, `wmsfind` searches the WMS database installed with the product. Using the optional `Version` parameter, you can search a database from a previous release or search a version of the WMS database hosted on the Mathworks website. The information

found in the installed database is static and is not automatically updated—it was validated at the time of the software release. The web-hosted database provides more up-to-date information about servers because it is updated regularly. Note, however, that searching the web-hosted database requires a connection to the Internet.

`wmsfind` returns `layers`, an array of `WMSLayer` objects containing one object for each layer whose name or title partially matches `querystr`. WMS servers produce maps of spatially referenced raster data, such as temperature or elevation, that are known as layers.

`layers = wmsfind(querystr, Name, Value)` modifies the search of the WMS database based on the values of the parameters. You can abbreviate parameter names, and case does not matter.

Input Arguments

querystr — Characters to search for in WMS database fields

character vector | cell array of character vectors | string | array of strings

Characters to search for in WMS database fields, specified as a character vector, cell array of character vectors, string, or array of strings. `querystr` can contain the asterisk wildcard character (*).

Example: 'temperature'

Data Types: char | cell | string

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name, Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`.

IgnoreCase — Ignore case when comparing field values to querystr

true (default) | false

Ignore case when comparing field values to `querystr`, specified as the logical value `true` or `false`.

Data Types: logical

Latlim — Latitudinal limits of the search

two-element numeric vector | numeric scalar

Latitudinal limits of the search, specified as a two-element vector of the form [southern_limit northern_limit] or a scalar value representing the latitude of a single point. Values are in the range [-90, 90]. All angles are in units of degrees. If provided and not empty, a given layer appears in the results only if its limits fully contain the specified 'Latlim' limits. Partial overlap does not result in a match.

Data Types: double | int16 | int32 | int64 | int8 | single | uint8 | uint16 | uint32 | uint64

Lonlim — Longitudinal limits of the search

two-element numeric vector | numeric scalar

Longitudinal limits of the search, specified as a two-element vector of the form [western_limit eastern_limit] or scalar value representing the longitude of a single point. All angles are in units of degrees. If provided and not empty, a given layer appears in the results only if its limits fully contain the specified 'Lonlim' limits. Partial overlap does not result in a match.

Data Types: double | int16 | int32 | int64 | int8 | single | uint8 | uint16 | uint32 | uint64

MatchType — Strictness of match

'partial' (default) | 'exact'

Strictness of match, specified as the character vector or string 'partial' or 'exact'. If 'MatchType' is 'exact' and querystr is '*', a match occurs when the search field matches the character '*'.

Data Types: char | string

SearchFields — Fields to search in the WMS database

'layer' (default) | 'server' | 'layertitle' | 'layername' | 'servertitle' | 'serverurl' | 'any'

Fields to search in the WMS database, specified as a character vector, cell array of character vectors, string, or array of strings. The function searches the values of the specified fields in the WMS database for a partial or exact match with querystr. The following table lists valid values.

| Field | Behavior |
|---------------|--|
| 'layername' | Search the LayerName field in the WMS database. The layer name is an abbreviated form of the LayerTitle field and is the keyword the server uses to retrieve the layer. |
| 'layertitle' | Search the LayerTitle field in the WMS database. The layer title includes descriptive information about a layer and facilitates understanding the meaning of the raster values of the layer. |
| 'layer' | Search both the LayerTitle and the LayerName fields. |
| 'servertitle' | Search the ServerTitle field in the WMS database. A server title includes descriptive information about the server. |
| 'serverurl' | Search the ServerURL field in the WMS database. The server URL and layer information facilitate the reading of raster layers by the function wmsread. |
| 'server' | Search both the ServerTitle and the ServerURL fields. |
| 'any' | Search all fields. |

Data Types: char | cell | string

Version — Version of the WMS database to read

'installed' (default) | 'online' | 'custom'

Version of the WMS database to read, specified as one of the following strings or character arrays.

| Value | Description |
|-------------|---|
| 'installed' | Read from the installed database. This is the default. The information found in the installed database is static and is not automatically updated—it was validated at the time of the software release. |

| Value | Description |
|----------|---|
| 'online' | Read from the version of the database hosted on the MathWorks website. This version of the database contains more up-to-date information about servers because it is updated regularly. Note, however, that searching this online database requires a connection to the Internet. |
| 'custom' | Read from the <code>wmsdatabase.mat</code> file on the MATLAB path, such as from a previous release. |

Data Types: `char` | `string`

Output Arguments

Layers — Layers that match search criteria

Layers that match search criteria, returned as an array of `WMSLayer` objects, one for each layer found.

Examples

Search the WMS Database for Layers

Search the Entire WMS Database

Search the WMS database for layers that contain the word "temperature". The `wmsfind` function returns an array of `WMSLayer` objects.

```
layers = wmsfind('temperature');
```

Find layers that contain global temperature data. The query includes the asterisk wildcard character "*".

```
layers = wmsfind('global*temperature');
```

Search Specific Fields in the WMS Database

Search the `LayerTitle` field for all layers that contain an exact match for the term 'Rivers'. You must use the `MatchType` parameter to specify an exact match.

```
layers = wmsfind('Rivers', 'MatchType', 'exact', ...
                'IgnoreCase', false, 'SearchFields', 'layertitle');
```

Search the LayerName field for all layers that contain a partial match for 'elevation'. By default, wmsfind searches for partial matches.

```
layers = wmsfind('elevation', 'SearchFields', 'layername');
```

Search the LayerName field for all unique servers that contain 'BlueMarbleNG'.

```
layers = wmsfind('BlueMarbleNG', 'SearchFields', 'layername', ...
                'MatchType', 'exact');
urls = servers(layers);
```

Limit Your Search to Specific Geographic Regions

Find layers that contain elevation data for Colorado. Use the Latlim and Lonlim parameters to specify the location.

```
latlim = [35 43];
lonlim = [-111 -101];
layers = wmsfind('elevation', 'Latlim', latlim, 'Lonlim', lonlim);
```

Find all layers that contain temperature data for a point in Perth, Australia. Use the Latlim and Lonlim parameters to specify the location.

```
lat = -31.9452;
lon = 115.8323;
layers = wmsfind('temperature', 'Latlim', lat, 'Lonlim', lon);
```

Find all the layers provided by servers located at the Jet Propulsion Laboratory (JPL).

```
layers = wmsfind('jpl.nasa.gov', 'SearchFields', 'serverurl');
```

Find all the unique URLs of all government servers.

```
layers = wmsfind('*.gov*', 'SearchFields', 'serverurl');
urls = servers(layers);
```

Search Multiple Fields at the Same Time and Refine Your Search

Search both the LayerTitle and the LayerName fields for all the layers that contain the word "temperature".

```
fields = [string('layertitle') string('layername')];
temperature = wmsfind('temperature', 'SearchFields', fields);
```

Refine the results of your temperature search to find only those layers that deal with sea surface temperatures. Use the `WMSLayer` object `refine` method.

```
sst = refine(temperature, 'sea surface');
```

Refine your sea surface temperature search further to find only those layers that deal with global sea surface temperatures.

```
global_sst = refine(sst, 'global');
```

Search the Entire WMS Database and Progressively Refine Your Search

Note that finding all the layers from the WMS database may take several seconds to execute and require a substantial amount of memory. The database contains more than 100,000 layers.

Find all the layers in the WMS database and sort them into a set that comprises only the unique layer titles.

```
layers = wmsfind('*');  
layerTitles = sort(unique({layers.LayerTitle}));
```

Refine your original search, `layers`, to include only those layers with global coverage. Use the `WMSLayer` object `refineLimits` method.

```
global_layers = refineLimits(layers, ...  
                             'Latlim', [-90 90], 'Lonlim', [-180 180]);
```

Refine the results of your global layers search to contain only layers with global extent that include the word "topography". Use the `WMSLayer` object `refine` method.

```
global_topography_layers = refine(global_layers, 'topography');
```

Refine your original search, `layers`, to contain only layers that have some combination of the terms "oil" and "gas" in the `LayerTitle` field.

```
oil_gas_layers = refine(layers, 'oil*gas', 'SearchFields', 'layertitle');
```

Search Most Recent Online Version of WMS Database

Search the most recent online version of the WMS database for layers that contain the word "elevation". Use the `Version` parameter, specifying the value 'online'.

```
elevation = wmsfind('elevation', 'Version', 'online')
```

Tips

- The `WMSLayer` objects returned by `wmsfind` contain properties with the same names as the field names of the WMS database, along with three additional properties: `'Abstract'`, `'CoordRefSysCodes'`, and `'Details'`. The WMS database does not contain information about these properties. To get this information about a server, you must use the `wmsupdate` function which updates these properties of the `WMSLayer` object by downloading information from the server. To view these properties, use the `WMSLayer.disp` method, specifying the `'Properties'` parameter value `'all'`. If you want to know more about a WMS server, use the `wmsinfo` function with the specific server URL.

See Also

`WMSLayer` | `wmsinfo` | `wmsread` | `wmsupdate`

Topics

“Troubleshoot Access to the Hosted WMS Database”

Introduced in R2009b

wmsinfo

Information about WMS server from capabilities document

Syntax

```
[capabilities, infoRequestURL] = wmsinfo(serverURL)
[capabilities, infoRequestURL] = wmsinfo(infoRequestURL)
[capabilities, infoRequestURL] = wmsinfo( ____, Name, Value)
```

Description

[capabilities, infoRequestURL] = wmsinfo(serverURL) accesses the Internet to read a capabilities document from a Web Map Service (WMS) server. A capabilities document is an XML document that contains metadata describing the geographic content offered by the server. The wmsinfo function returns the contents of the capabilities document into capabilities, a WMSCapabilities object. The WMS server URL serverURL contains the protocol 'http://' or 'https://' and additional WMS or access keywords. You can insert the URL character vector infoRequestURL, composed of the serverURL with additional WMS parameters, into a browser or urlread to return the XML capabilities document. The wmsinfo function requires an Internet connection. Periodically, the WMS server is unavailable. Retrieving the map can take several minutes.

[capabilities, infoRequestURL] = wmsinfo(infoRequestURL) reads the capabilities document from a WMS infoRequestURL and returns the contents into capabilities.

[capabilities, infoRequestURL] = wmsinfo(____, Name, Value) specifies a parameter-value pair that modifies the request to the server.

Input Arguments

serverURL

WMS server URL that contains the protocol 'http://' or 'https://' and additional WMS or access keywords.

Name-Value Pair Arguments

Specify optional comma-separated pairs of `Name`, `Value` arguments. `Name` is the argument name and `Value` is the corresponding value. `Name` must appear inside single quotes (' '). You can specify several name and value pair arguments in any order as `Name1,Value1, . . . ,NameN,ValueN`.

You can abbreviate the parameter name, which is case-insensitive.

TimeoutInSeconds

Integer-valued, scalar double that indicates the number of seconds to elapse before a server times out. A value of 0 causes the time-out mechanism to be ignored.

Default: 60 seconds

Output Arguments

capabilities

WMSCapabilities object.

Default:

infoRequestURL

URL composed of the `serverURL` with additional WMS parameters, returned as a character vector.

Examples

Use `wmsinfo` to read a capabilities document and display the abstract of the first layer.

```
% Read the capabilities document from the NASA Goddard
% Space Flight Center WMS server.
serverURL = 'http://svs.gsfc.nasa.gov/cgi-bin/wms?';
capabilities = wmsinfo(serverURL);

% Display the layer information in the command window.
capabilities.Layer
```

Sample output follows:

```
Index: 304
ServerTitle: 'NASA SVS Image Server'
ServerURL: 'http://svs.gsfc.nasa.gov/cgi-bin/wms?'
LayerTitle: '(4096x2048 Animation)'
LayerName: '3348_27724'
Latlim: [-90.0000 90.0000]
Lonlim: [-180.0000 180.0000]
Abstract: 'NASA's Aqua satellite was launched ...'
CoordRefSysCodes: {'CRS:84'}
Details: [1x1 struct]
```

```
% Refine the list to include only layers with the term
% "glacier retreat" in the LayerTitle.
glaciers = capabilities.Layer.refine('glacier retreat', ...
    'SearchFields', 'LayerTitle');
```

```
% Display the abstract of the first layer.
glaciers(1).Abstract
```

Sample output follows:

Since measurements of Jakobshavn Isbrae were first taken....

Tips

- To specify a proxy server to connect to the Internet, select **File>Preferences>Web** and enter your proxy information. Use this feature if you have a firewall.
- `wmsinfo` communicates with the server using a `WebMapServer` object representing an implementation of a WMS specification. The object acts as a proxy to a WMS server and resides physically on the client side. The object accesses the server's capabilities document. The object supports multiple WMS versions and negotiates with the server to use the highest known version that the server can support. The object automatically times-out after 60 seconds if a connection is not made to the server.

See Also

Functions

`wmsfind` | `wmsread` | `wmsupdate`

Objects

WMSCapabilities | WMSLayer | WebMapServer

Introduced in R2009b

WMSLayer

Web Map Service layer

Description

A `WMSLayer` object describes a Web Map Service (WMS) layer or layers.

Creation

You can create a `WMSLayer` object using any of the following methods:

- `wmsfind` — Returns a `WMSLayer` array.
- `wmsinfo` — Returns a `WMSCapabilities` object, which contains an array of `WMSLayer` objects in its `Layer` property.
- The `WMSLayer` object creation function, described here.

```
layers = WMSLayer(Name, Value, ...)
```

Description

`layers = WMSLayer(Name, Value, ...)` constructs a `WMSLayer` object, where `Name` is the name of any property of the `WMSLayer` and `Value` is the value that you want to assign to the property. You can specify several name-value pair arguments in any order as `Name1, Value1, ..., NameN, ValueN`. The size of the output `layers` is scalar unless all inputs are cell arrays, in which case, the size of `layers` matches the size of the cell arrays.

Properties

ServerTitle — Descriptive information about the server

empty character vector (' ') (default) | character vector

Descriptive information about the server, specified as a character vector.

Data Types: char

ServerURL — URL of WMS Server

empty character vector (' ') (default) | character vector

URL of WMS Server, specified as a character vector.

Data Types: char

LayerTitle — Descriptive information about the layer

empty character vector (' ') (default) | character vector

Descriptive information about the layer, specified as a character vector. The `LayerTitle` clarifies the meaning of the raster values of the layer.

Data Types: char

LayerName — Keyword the server uses to retrieve the layer

empty character vector (' ') (default) | character vector

Keyword the server uses to retrieve the layer, specified as a character vector.

Data Types: char

LatLim — Latitude limits of the layer in units of degrees

[] (default) | two-element numeric vector

Latitude limits of the layer in units of degrees, specified as a two-element numeric vector. The limits specify the southern and northern latitude limits and must be in units of degrees and in the range [-90, 90].

Data Types: double

LonLim — Longitude limits of the layer in units of degrees

[] (default) | two-element numeric vector

Longitude limits of the layer in units of degrees, specified as a two-element numeric vector. The limits specify the western and eastern longitude limits and must be ascending and in the range [-180, 180] or [0, 360].

Data Types: double

Abstract — Information about the layer

empty character vector (' ') (default) | character vector

Information about the layer, specified as a character vector.

Data Types: `char`

CoordRefSysCodes — Codes identifying available coordinate reference systems

empty cell array `{}` (default) | cell array of character vectors

Codes identifying available coordinate reference systems, specified as a cell array of character vectors.

Data Types: `cell`

Details — Detailed information about the layer

`struct`

Detailed information about the layer, specified as a structure containing: `MetadataURL`, `Attributes`, `Scale`, `Dimension`, `Style`. See the `WMSLayer.Details` on page 1-1590 reference page for more information.

Data Types: `struct`

Object Functions

| | |
|---------------------------|--|
| <code>disp</code> | Display properties of WMS layers or capabilities |
| <code>refine</code> | Refine search of WMS layers |
| <code>refineLimits</code> | Refine search of WMS layers based on geographic limits |
| <code>servers</code> | Return URLs of unique WMS servers |
| <code>serverTitles</code> | Return titles of unique WMS servers |

Examples

Construct WMSLayer Object from WMS GetMap Request URL

Specify the server URL. These values are typically found during an Internet search. The `WMSLayer.ServerURL` value is obtained from the host and path of the request URL. The `WMSLayer.LayerName` value is obtained from the `LAYERS` value in the query part of the URL.

```
host = 'raster.nationalmap.gov';  
path = '/arcgis/services/LandCover/USGS_EROS_LandCover_NLCD/MapServer/WMSServer?';
```

```

serverURL = ['http://' host path];
requestURL = [serverURL 'SERVICE=WMS&FORMAT=image/jpeg&REQUEST=GetMap&' ...
              'STYLES=&SRS=EPSG:4326&VERSION=1.1.1&LAYERS=33&', ...
              'WIDTH=1024&HEIGHT=470&BBOX=-128,23,-65,51'];
layerName = '33';

```

Construct the WMSLayer object by using the serverURL variable and the value of the WMS LAYERS parameter.

```
layer = WMSLayer('ServerURL', serverURL, 'LayerName', layerName);
```

Use the wmsupdate function to get the other properties of the WMSLayer array from the server. The National Map Server may be busy, so try several times.

```

updatedLayer = wmsupdate(layer);
if isempty(updatedLayer)
    numAttempts = 1;
    maxAttempts = 10;
    delay = 1;
    while isempty(updatedLayer) && numAttempts < maxAttempts
        updatedLayer = wmsupdate(layer);
        pause(delay)
        numAttempts = numAttempts + 1;
    end
end
layer = updatedLayer;

```

Retrieve an image from the WMS server using layer and parameter values from the WMS GetMap request URL. Set latitude and longitude limits from the BBOX request value. Set image height and width values from the WIDTH and HEIGHT request values.

```

lonlim = [-128 -65];
latlim = [23 51];
height = 470;
width = 1024;
[A, R] = wmsread(layer, 'Latlim', latlim, 'Lonlim', lonlim, ...
                'ImageHeight', height, 'ImageWidth', width);

```

Display the image from the server.


```

figure
usamap(A, R)
geoshow(A, R)
title(layer.LayerTitle, 'Interpreter', 'none')

```

The image can also be retrieved using the WMS requestURL.

```
[A, R] = wmsread(requestURL);
```



Courtesy of U.S. Geological Survey

- “Update Your Layer”

See Also

Functions

[wmsfind](#) | [wmsinfo](#) | [wmsread](#) | [wmsupdate](#)

Objects

[WMSCapabilities](#) | [WMSMapRequest](#) | [WebMapServer](#)

Topics

“Update Your Layer”

Introduced in R2009b

Details property

Description

A structure containing detailed information about a layer

Details Structure

| Field Name | Data Type | Field Content |
|----------------------------|------------------|---|
| MetadataURL | Character vector | URL containing metadata information about layer. |
| Attributes on page 1-1591 | Structure | Attributes of layer. |
| BoundingBox on page 1-1591 | Structure array | Bounding box of layer. |
| Dimension on page 1-1592 | Structure array | Dimensional parameters of layer, such as time or elevation. |
| ImageFormats | Cell array | Image formats supported by server. |
| ScaleLimits on page 1-1593 | Structure | Scale limits of layer. |
| Style on page 1-1593 | Structure array | Style parameters that determine layer rendering. |
| Version | Character vector | WMS version specification. |

Attributes Structure

| Field Name | Data Type | Field Content |
|-------------|-----------|--|
| Queryable | Logical | True if you can query the layer for feature information. |
| Cascaded | Double | Number of times a Cascading Map server has retransmitted the layer. |
| Opaque | Logical | True if the map data are mostly or completely opaque. |
| NoSubsets | Logical | True if the map must contain the full bounding box. false if the map can be a subset of the full bounding box. |
| FixedWidth | Logical | True if the map has a fixed width that the server cannot change. false if the server can resize the map to an arbitrary width. |
| FixedHeight | Logical | True if the map has a fixed height that the server cannot change. false if the server can resize the map to an arbitrary height. |

BoundingBox Structure

| Field Name | Data Type | Field Content |
|-----------------|------------------|---|
| CoordRefSysCode | character vector | Code number for coordinate reference system. |
| XLim | Double array | X limit of layer in units of coordinate reference system. |
| YLim | Double array | Y limit of layer in units of coordinate reference system. |

Dimension Structure

| Field Name | Data Type | Field Content |
|-------------------|------------------|--|
| Name | Character vector | Name of the dimension; such as time, elevation, or temperature. |
| Units | Character vector | Measurement unit. |
| UnitSymbol | Character vector | Symbol for unit. |
| Default | Character vector | Default dimension setting. For example, if default is 'time' and dimension is not specified, server returns time holding. |
| MultipleValues | Logical | True if multiple values of the dimension may be requested. false if only single values may be requested. |
| NearestValue | Logical | True if nearest value of dimension is returned in response to request for nearby value. false if request value must correspond exactly to declared extent values. |
| Current | Logical | True if temporal data are kept current (valid only for temporal extents). |
| Extent | Character vector | Values for dimension. Expressed in any of the following ways: <ul style="list-style-type: none">• Single value (value)• List of values (value1, value2, ...)• Interval defined by bounds and resolution (min1/max1/res1)• List of intervals (min1/max1/res1, min2/max2/res2, ...) |

ScaleLimits Structure

| Field Name | Data Type | Field Content |
|---------------------|--------------|---|
| ScaleHint | Double array | Minimum and maximum scales for which it is appropriate to display layer. Expressed as scale of ground distance in meters represented by diagonal of central pixel in image. |
| MinScaleDenominator | Double | Minimum scale denominator of maps for which a layer is appropriate. |
| MaxScaleDenominator | Double | Maximum scale denominator of maps for which a layer is appropriate. |

Style Structure Array

| Field Name | Data Type | Field Content |
|--------------------------|------------------|------------------------------------|
| Title | Character vector | Descriptive title of style. |
| Name | Character vector | Name of style. |
| Abstract | Character vector | Information about style. |
| LegendURL on page 1-1593 | Structure | Information about legend graphics. |

LegendURL Structure

| Field Name | Data Type | Field Content |
|----------------|------------------|----------------------------|
| OnlineResource | Character vector | URL of legend graphics. |
| Format | Character vector | Format of legend graphics. |
| Height | Double | Height of legend graphics. |
| Width | Double | Width of legend graphics. |

WMSMapRequest

Web Map Service map request

Description

A `WMSMapRequest` object contains a request to a WMS server to obtain a map, which represents geographic information. The WMS server renders the map as a color or grayscale image. The object contains properties that you can set to control the geographic extent, rendering, or size of the requested map.

Creation

You can

```
mapRequest = WMSMapRequest(layer)
mapRequest = WMSMapRequest(layer, server)
```

Description

`mapRequest = WMSMapRequest(layer)` creates a `WMSMapRequest` object, setting the `Layer` property. The `WMSMapRequest` object updates the properties of `Layer`, if necessary.

`mapRequest = WMSMapRequest(layer, server)` creates a `WMSMapRequest` object, setting the `Layer` and `Server` properties. The `ServerURL` property of `layer` must match the `ServerURL` property of `server`. The `Server` object updates `Layer` properties.

Properties

Server — Web map server

scalar `WebMapServer` object

Web map server, specified as a scalar `WebMapServer` object. If a server is not supplied as an argument when creating the `WMSMapRequest`, the value of `Server` is set to the `ServerURL` of `Layer`.

Layer — Web Map Service layers

array of `WMSLayer` objects

Web Map Service layers, specified as an array of `WMSLayer` objects.

`Layer` contains one unique `ServerURL`, which must match the `ServerURL` property of `Server`. The `Server` property updates the properties of `Layer` when the property is set.

CoordRefSysCode — Coordinate reference system code

'CRS:84' | 'EPSG:4326'

Coordinate reference system code, specified as the character vector 'CRS:84' for WMS version 1.3.x, and 'EPSG:4326' for all other versions.

- If 'EPSG:4326' is not found in `Layer.CoordRefSysCodes`, then the `CoordRefSysCode` value is set from the first `CoordRefSysCode` found in the `Layer.Details.BoundingBox` structure array.
- When `CoordRefSysCode` is set to 'EPSG:4326' or 'CRS:84', the `XLim` and `YLim` properties are set to [] and the `LatLim` and `LonLim` properties are set to the geographic extent defined by the `Layer` array.
- When `CoordRefSysCode` is set to a value other than 'EPSG:4326' or 'CRS:84', then the `XLim` and `YLim` properties are set from the values found in the `Layer.Details.BoundingBox` structure and the `LatLim` and `LonLim` properties are set to [].
- Automatic projections are not supported. (Automatic projections begin with 'AUTO'.)

Data Types: char

RasterReference — Map or geographic raster reference

`MapCellsReference` or `GeographicCellsReference`

Map or geographic raster reference, specified as a `MapCellsReference` or `GeographicCellsReference` object. `RasterReference` references the raster map to an intrinsic coordinate system

LatLim — Latitude limits

two-element vector

Latitude limits, specified as a two-element vector. `LatLim` contains the southern and northern latitudinal limits of the request in units of degrees. The limits must be ascending. By default, the latitude limits span all latitudinal limits found in the `Layer.LatLim` property.

LonLim — Longitude limits

two-element vector

Longitude limits, specified as a two-element vector. `LonLim` contains the western and eastern longitudinal limits of the request in units of degrees. The limits must be ascending and in the range [-180, 180] or [0, 360]. By default, the longitude limits span all longitudinal limits found in the `Layer.LonLim` property.

XLim — Western and eastern limits in the units of the coordinate reference system

[] (default) | two-element vector

Western and eastern limits of the requested map in the units of the coordinate reference system, specified as a two-element vector. The limits must be ascending. You can set `XLim` only if you set `CoordRefSysCode` to a value other than `EPSG:4326`.

YLim — Southern and northern in the units of the coordinate reference system

[] (default) | two-element vector

Southern and northern limits of the requested map in the units of the coordinate reference system, specified as a two-element vector. The limits must be ascending. You can set `YLim` only if you set `CoordRefSysCode` to a value other than `EPSG:4326`.

ImageHeight — Height in pixels for the requested raster map

positive integer

Height in pixels for the requested raster map, specified as a positive integer. The property `MaximumHeight` defines the maximum value for `ImageHeight`. The `WMSMapRequest` object initializes the `ImageHeight` property to either 512 or to an integer value that best preserves the aspect ratio of the coordinate limits, without changing the coordinate limits.

ImageWidth — Width in pixels for the requested raster map

positive integer

Width in pixels for the requested raster map, specified as a positive integer. The property `MaximumWidth` defines the maximum value for `ImageWidth`. The `WMSMapRequest`

object initializes the `ImageWidth` property to either 512 or to an integer value that best preserves the aspect ratio of the coordinate limits, without changing the coordinate limits.

MaximumHeight — Maximum height in pixels of requested map

8192

This property is read-only.

Maximum height in pixels for the requested map, specified as the number 8192.

Data Types: `double`

MaximumWidth — Maximum width in pixels of requested map

8192

This property is read-only.

Maximum width in pixels for the requested map, specified as the number 8192.

Data Types: `double`

Elevation — Elevation extent of requested map

' ' (default) | character vector

Elevation extent of the requested map, specified as a character vector. When you set the property, 'elevation' must be the value of the `Layer.Details.Dimension.Name` field.

Time — Time extent of requested map

character vector | numeric scalar

Time extent of the requested map, specified as a character vector or numeric scalar. See the `WMSMapRequest.Time` on page 1-1605 reference page for more information.

Data Types: `double` | `char`

SampleDimension — Name and value of a sample dimension

two-element cell array of character vectors

Name and value of a sample dimension, specified as a two-element cell array of character vectors. The name cannot be 'time' or 'elevation'. `SampleDimension{1}` must be the value of the `Layer.Details.Dimension.Name` field.

Transparent — Flag indicating transparency of map background

false (default) | logical scalar

Flag indicating transparency of map background, specified as a logical scalar. When you set `Transparent` to `true`, the server sets all pixels not representing features or data values in that layer to a transparent value, producing a composite map. When you set `Transparent` to `false`, the server sets all non-data pixels to the value of the background color.

Data Types: `logical`

BackgroundColor — Color of the background (non-data) pixels of the map

three-element numeric vector

Color of the background (non-data) pixels of the map, specified as a three-element numeric vector. The values range from 0 to 255. The default value, `[255,255,255]`, specifies the background color as white. You can set `BackgroundColor` using `non-uint8` numeric values, but they are cast and stored as `uint8`.

Data Types: `uint8`

StyleName — Style to use when rendering the image

{ } (default) | character vector or cell array of character vectors

Style to use when rendering the image, specified as a character vector or cell array of character vectors. The `StyleName` must be a valid entry in the `Layer.Details.StyleName` field. The cell array of character vectors contains the same number of elements as does `Layer`.

ImageFormat — Desired image format used to render the map as an image

character vector

Desired image format used to render the map as an image, specified as a character vector. If set, the format must match an entry in the `Layer.Details.ImageFormats` cell array and an entry in the `ImageRenderFormats` property. If not set, the format defaults to a value in the `ImageRenderFormats` property.

ImageRenderFormats — Preferred image rendering formats when `Transparent` is set to `false`

cell array

This property is read-only.

Preferred image rendering formats when `Transparent` is set to `false`, specified as a cell array. The first entry is the most preferred image format. If the preferred format is not stored in the `Layer` property, then the next format from the list is selected, until a format is found. The `ImageRenderFormats` array is not used if the `ImageFormat` property is set.

ImageTransparentFormats — Preferred image rendering formats when Transparent is set to true

cell array

This property is read-only.

Preferred image rendering formats when `Transparent` is set to `true`, specified as a cell array. The first entry is the most preferred image format. If the preferred format is not stored in the `Layer` property, then the next format from the list is selected, until a format is found. If a transparent image format is not found in the list, or if the `ImageFormat` property is set to a non-default value, then `ImageFormat` is unchanged.

ServerURL — Server URL for the WMS GetMap request

character vector

Server URL for the WMS GetMap request, specified as a character vector. In general, `ServerURL` matches the `ServerURL` of the `Layer`. However, some WMS servers, such as the Microsoft® TerraServer, require a different URL for GetMap requests than for WMS GetCapabilities requests. By default, `ServerURL` is `Layer(1).ServerURL`.

Data Types: `char`

RequestURL — Full URL for the WMS GetMap request

character vector

This property is read-only.

Full URL for the WMS GetMap request, specified as a character vector. It is composed of the `ServerURL` with additional WMS parameter/value pairs.

Object Functions

`boundImageSize` Bound size of raster map

Examples

Read Global Sea-Surface Temperature Map from NASA Server

Read a global, half-degree resolution, sea-surface temperature map for the month of November 2009. The map, from the AMSR-E sensor on NASA's Aqua satellite, uses data provided by NASA's Earth Observations (NEO) WMS server.

```
sst = wmsfind('AMSRE_SSTAn_M');
server = WebMapServer(sst.ServerURL);
mapRequest = WMSMapRequest(sst, server);
timeRequest = '2009-11-01';
mapRequest.Time = timeRequest;
samplesPerInterval = .5;
mapRequest.ImageHeight = ...
    round(abs(diff(sst.Latlim))/samplesPerInterval);
mapRequest.ImageWidth = ...
    round(abs(diff(sst.Lonlim))/samplesPerInterval);
mapRequest.ImageFormat = 'image/png';
sstImage = server.getMap(mapRequest.RequestURL);
```

Read the legend for the layer using the OnlineResource URL field in the LegendURL structure. The legend shows that the temperature ranges from -2 to 35 degrees Celsius. The WMSMapRequest object updates the layer information from the server.

```
url = mapRequest.Layer.Details.Style(1).LegendURL.OnlineResource;
[legendImg,cmap] = imread(url);
if ~isempty(cmap)
    % Convert indexed image to RGB.
    legendRGB = ind2rgb(legendImg,cmap);
else
    % Already have an RGB image.
    legendRGB = legendImg;
end
```


Display the temperature map and legend.

```
fig = figure;
ax = worldmap('world');
setm(ax, 'MlabelParallel', -90, 'MlabelLocation', 90)
geoshow(sstImage, mapRequest.RasterReference);
title({mapRequest.Layer.LayerTitle, timeRequest})
```

```
figurePosition = fig.Position;  
centerWidth = figurePosition(3)/2;  
axleft = centerWidth-size(legendImg,2)/2;  
axbottom = 30;  
axwidth = size(legendRGB,2);  
axheight = size(legendRGB,1);  
axes('Units','pixels','Position',[axleft axbottom axwidth axheight])  
image(legendRGB)  
axis off
```

Sea Surface Temperature Anomaly 2002-2011 (1 month - Aqua/AMSR-E)

2009-11-01



Read abstract information for this layer from the MetadataURL field.

```
options = weboptions('ContentType','xml', 'Timeout',10);
xml = webread(mapRequest.Layer.Details.MetadataURL,options);
abstract = xml.getElementsByTagName('abstract').item(0).getTextContent
```


Read and Display Global Elevation and Bathymetry Layer

Read and display a global elevation and bathymetry layer for the Gulf of Maine at 30 arc-seconds sampling interval. The values are in units of meters.

```
layers = wmsfind('srtm30', 'SearchField', 'LayerName');
layer = refine(layers, 'data.worldwind', 'SearchField', 'serverurl');
server = WebMapServer(layer.ServerURL);
mapRequest = WMSMapRequest(layer,server);
mapRequest.Latlim = [40 46];
mapRequest.Lonlim = [-71 -65];
samplesPerInterval = 30/3600;
mapRequest.ImageHeight = ...
    round(abs(diff(mapRequest.Latlim))/samplesPerInterval);
mapRequest.ImageWidth = ...
    round(abs(diff(mapRequest.Lonlim))/samplesPerInterval);
mapRequest.ImageFormat = 'image/bil';
Z = getMap(server, mapRequest.RequestURL);
```

Display and contour the map at sea level (0 meters).

```
figure
worldmap(mapRequest.Latlim, mapRequest.Lonlim)
geoshow(double(Z),mapRequest.RasterReference,'DisplayType','texturemap')
demcmap(double(Z))
contourm(double(Z),mapRequest.RasterReference,[0 0],'Color','black')
colorbar
title({'Gulf of Maine', mapRequest.Layer.LayerTitle}, ...
      'Interpreter', 'none', 'FontWeight', 'bold')
```



See Also

Functions

wmsfind | wmsinfo | wmsread

Objects

WMSCapabilities | WMSLayer | WebMapServer

Introduced in R2009b

Time property

Requested time extent

Description

The `WMSMapRequest.Time` property stores time as a character vector or a `double` indicating the desired time extent of the requested map. When you set the property, 'time' must be the value of the `Layer.Details.Dimension.Name` field. The default value is ''.

Time is stored in the ISO® 8601:1988(E) extended format. In general, the `Time` property is stored in a `yyyy-mm-dd` format or a `yyyy-mm-ddThh:mm:ssZ` format, if the precision requires hours, minutes, or seconds. You can use several different character vector and numeric formats to set the `Time` property, according to the following table (where dateform number is the number used by the Standard MATLAB Date Format Definitions). Express all hours, minutes, and seconds in Coordinated Universal Time (UTC).

| Dateform (number) | Input (character vector) | Stored format |
|-------------------|--------------------------|---------------------------|
| 0 | dd-mm-yyyy HH:MM:SS | yyyy-mm-ddTHH:MM:SSZ |
| 1 | dd-mm-yyyy | yyyy-mm-dd |
| 2 | mm/dd/yy | yyyy-mm-dd |
| 6 | mm/dd | yyyy-mm-dd (current year) |
| 10 | YYYY | YYYY |
| 13 | HH:MM:SS | yyyy-mm-ddTHH:MM:SSZ |
| 14 | HH:MM:SS PM | yyyy-mm-ddTHH:MM:SSZ |
| 15 | HH:MM | yyyy-mm-ddTHH:MM:00Z |
| 16 | HH:MM PM | yyyy-mm-ddTHH:MM:00Z |
| 21 | mmm.dd, yyyy HH:MM:SS | yyyy-mm-ddTHH:MM:SSZ |
| 22 | mmm.dd, yyyy | yyyy-mm-dd |
| 23 | mm/dd/yyyy | yyyy-mm-dd |

| Dateform (number) | Input (character vector) | Stored format |
|--------------------------|---------------------------------|----------------------|
| 26 | yyyy/mm/dd | yyyy-mm-dd |
| 29 | yyyy-mm-dd | yyyy-mm-dd |
| 30 | yyyymmddTHHMMSS | yyyy-mm-ddTHH:MM:SSZ |
| 31 | yyyy-mm-dd HH:MM:SS | yyyy-mm-ddTHH:MM:SSZ |

Inputs using the dateform numbers 13–16 return the date set to the current year, month, and day. Use of other dateform formats, especially 19, 20, 24, and 25, results in erroneous output.

In addition to these standard MATLAB dateform formats, the `WMSMapRequest.Time` property also accepts the following inputs.

| Input (character vector) | Description |
|---------------------------------|---|
| 'current' | The current time holdings of the server |
| numeric datenum | Numeric date value converted to yyyy-mm-dd (dateform 29 format) |
| Byyyy | B.C.E. year |

Use the prefixes K, M, and G, followed by a character vector number (thousand, million, and billion years, respectively), for geologic data sets that refer to the distant past.

wmsread

Retrieve WMS map from server

Syntax

```
[A,R] = wmsread(layer)
[A,R] = wmsread(layer,Name,Value,...)
[A,R] = wmsread(mapRequestURL)
[A,R,mapRequestURL] = wmsread(...)
```

Description

[A,R] = wmsread(layer) accesses the Internet to render and retrieve a raster map from a Web Map Service (WMS) server. The `ServerURL` property of the `WMSLayer` object, `layer`, specifies the server. If `layer` has more than one element, then the server overlays each subsequent layer on top of the base (first) layer, forming a single image. The server renders multiple layers only if all layers share the same `ServerURL` value.

The WMS server returns a raster map, either a color or grayscale image, in the output `A`. The second output, `R`, is a raster reference object that ties `A` to the EPSG:4326 geographic coordinate system on page 1-1618. The rows of `A` are aligned with parallels, with even sampling in longitude. Likewise, the columns of `A` are aligned with meridians, with even sampling in latitude.

The geographic limits of `A` span the full latitude and longitude extent of `layer`. The `wmsread` function chooses the larger spatial size of `A` to match its larger geographic dimension. The larger spatial size is fixed at the value 512. In other words, assuming RGB output, `A` is 512-by-`N`-by-3 if the latitude extent exceeds longitude extent and `N`-by-512-by-3 otherwise. In both cases `N` ≤ 512. The `wmsread` function sets `N` to the integer value that provides the closest possible approximation to equal cell sizes in latitude and longitude. The map spans the full extent supported for the `layer`.

[A,R] = wmsread(layer,Name,Value,...) specifies parameter-value pairs that modify the request to the server. You can abbreviate parameter names, which are case-insensitive.

[A,R] = wmsread(mapRequestURL) uses the input argument mapRequestURL to define the request to the server. The mapRequestURL contains a WMS serverURL with additional WMS parameters. These WMS parameters include BBOX, GetMap and the EPSG:4326 or CRS:84 keyword. Obtain a mapRequestURL from the output of wms read, the RequestURL property of a WSMMapRequest object, or an Internet search.


[A,R,mapRequestURL] = wms read (...) returns a WMS GetMap request URL in the character vector mapRequestURL. You can insert the mapRequestURL into a browser to make a request to a server, which then returns the raster map. The browser opens the returned map if its mime type is understood, or saves the raster map to disk.

Examples

Read and Display a Blue Marble Next Generation Layer from NASA

Read NASA layer and display it.

```
nasa = wmsfind('nasa', 'SearchField', 'serverurl');  
layer = nasa.refine('bluemarbleng', 'SearchField', 'layername', ...  
    'MatchType', 'exact');  
[A, R] = wmsread(layer(1));  
figure  
axesm globe  
axis off  
geoshow(A, R)  
title('Blue Marble')
```



Read and Display an Orthoimage

Read and display an orthoimage of the northern section of the Golden Gate Bridge in San Francisco, California, using the USGS National Map Seamless server.

Define region of interest.

```
latlim = [37.78 37.841];  
lonlim = [-122.53 -122.4];
```

Find the USGS high-resolution ortho-imagery layer. The USGS National Map provides ortho-imagery from various regions of the United States. One method to obtain the high-resolution ortho-imagery layer is to obtain the capabilities document from the server. The ortho-imagery layer is the only layer from this server. Use multiple attempts to connect to the server in case it is busy.

```
numberOfAttempts = 5;
attempt = 0;
info = [];
serverURL = 'http://basemap.nationalmap.gov/ArcGIS/services/USGSImageryOnly/MapServer/';
while(isempty(info))
    try
        info = wmsinfo(serverURL);
        orthoLayer = info.Layer(1);
    catch e


        attempt = attempt + 1;
        if attempt > numberOfAttempts
            throw(e);
        else
            fprintf('Attempting to connect to server:\n"%s"\n', serverURL)
        end
    end
end
```

Obtain the image and display it in a UTM projection.

```
imageLength = 1024;
[A, R] = wmsread(orthoLayer, 'Latlim', latlim, 'Lonlim', lonlim, ...
    'ImageHeight', imageLength, 'ImageWidth', imageLength);

figure
axesm('utm', 'Zone', utmzone(latlim, lonlim), ...
    'MapLatlimit', latlim, 'MapLonlimit', lonlim, ...
    'Geoid', wgs84Ellipsoid)
geoshow(A,R)
axis off
title({'San Francisco', 'Northern Section of Golden Gate Bridge'})
```

San Francisco Northern Section of Golden Gate Bridge




Read and Display Global Monthly Composite of Sea Surface Temperature

Read and display a global monthly composite of sea surface temperature for April 16, 2010 based on data from the AMSR-E sensor on board the Aqua satellite. Include the coastline, landmask, and nation layers.

```

coastwatch = wmsfind('coastwatch', 'SearchField', 'serverurl');
layers = coastwatch.refine('erdASstamday', ...
    'Searchfield','serverurl');
time = '2010-04-16T00:00:00Z';
[A, R] = wmsread(layers(end:-1:1), 'Time', time);
figure
axesm('pccarree', 'Maplonlimit', [0, 360], ...
    'PLabelLocation', 45, 'MLabelLocation', 90, ...
    'MLabelParallel', -90, 'MeridianLabel', 'on', ...
    'ParallelLabel', 'on');
geoshow(A, R);
title({layers(end).LayerTitle, time})

```



Input Arguments

Layer — Information about the layer you are retrieving

WMSLayer object

Information about the layer you are retrieving, specified as a WMSLayer object.

Example: [A,R] = wmsread(layers(1));

mapRequestURL — WMS GetMap request URL

character vector

WMS GetMap request URL, specified as a character vector.

Example: [A,R] = wmsread(mapURL);

Data Types: char

Name-Value Pair Arguments

Specify optional comma-separated pairs of Name, Value arguments. Name is the argument name and Value is the corresponding value. Name must appear inside single

quotes (' '). You can specify several name and value pair arguments in any order as Name1,Value1,...,NameN,ValueN.

Example: `[A,R] = wmsread(layers(1),'latlim',[40 50]);`

latlim — Latitude limits of the output image in degrees

[] (default) | two-element vector

Latitude limits of the output image in degrees, specified as a two-element vector of the form `[southern_limit northern_limit]`. The limit values must be ascending. By default, 'Latlim' is empty, and wmsread uses the full extent in latitude of layer. If `Layer.Details.Attributes.NoSubsets` is true, 'Latlim' may not be modified.

Example: `[A,R] = wmsread(layers(1),'latlim',[40 50]);`

Data Types: double

lonlim — Longitude limits of the output image in degrees

[] (default) | two-element vector

Longitude limits of the output image in degrees, specified as a two-element vector in the form `[western_limit eastern_limit]`. The limit values must be ascending. By default, 'Lonlim' is empty and the full extent in longitude of layer is used. If `Layer.Details.Attributes.NoSubsets` is true, you cannot modify 'Lonlim'

Example: `[A,R] = wmsread(layers(1),'lonlim',[40 50]);`

Data Types: double

ImageHeight — Desired height of the raster map in pixels

scalar, positive, integer-valued number

Desired height of the raster map in pixels, specified as a scalar, positive, integer-valued number. ImageHeight cannot exceed 8192. If `layer.Details.Attributes.FixedHeight` contains a positive number, you cannot modify 'ImageHeight'.

Example: `[A,R] = wmsread(layers(1),'ImageHeight',40);`

Data Types: double

ImageWidth — Desired width of the raster map in pixels

scalar, positive, integer-valued number

Desired width of the raster map in pixels, specified as a scalar, positive, integer-valued number. ImageWidth cannot exceed 8192. If

`Layer.Details.Attributes.FixedWidth` contains a positive number, you cannot modify `'ImageWidth'`.

Example: `[A,R] = wmsread(layers(1),'ImageWidth',100);`

Data Types: double

CellSize — Target size of the output pixels (raster cells) in degrees

scalar or two-element vector

Target size of the output pixels (raster cells) in degrees, specified as a scalar or two-element vector. If you specify a scalar, the value applies to both height and width dimensions. If you specify a vector, use the form `[height width]`. The `wmsread` function issues an error if you specify both `CellSize` and `ImageHeight` or `ImageWidth`. The output raster map must not exceed a size of `[8192,8192]`.

Example: `[A,R] = wmsread(layers(1),'Cellsize',5);`

Data Types: double

RelTolCellSize — Relative tolerance for 'CellSize'

.001 (default) | scalar or two-element vector

Relative tolerance for `'CellSize'`, specified as a scalar or two-element vector. If you specify a scalar, the value applies to both height and width dimensions. If you specify a vector, the tolerances appear in the order `[height width]`.

Example: `[A,R] = wmsread(layers(1),'RelTolCellsize',[4 5]);`

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64

ImageFormat — Desired format to use in rendering the map as an image

first available format in the in the `Layer.Details.ImageFormats` cell array (default) | character vector

Desired format to use in rendering the map as an image, specified as one of the following character vectors. If specified, the format must match an entry in the `Layer.Details.ImageFormats` cell array. If not specified, the format defaults to the first available format in the supported format list. .

| Value | Description |
|--------------|-------------|
| 'image/jpeg' | JPEG |

| Value | Description |
|------------------|---|
| 'image/gif' | GIF |
| 'image/png' | PNG |
| 'image/tiff' | TIFF |
| 'image/geotiff' | GeoTIFF |
| 'image/geotiff8' | GeoTIFF8 |
| 'image/tiff8' | TIFF8 |
| 'image/png8' | PNG8 |
| 'image/bil' | Band Interleaved by Line (BIL) format. When you specify the 'image/bil' format, wmsread returns A as a two-dimensional array with a class type of int16 or int32. |

Example: `[A,R] = wmsread(layers(1), 'ImageFormat', 'image/png');`

Data Types: char

StyleName — Style to use when rendering the image

' ' (default) | character vector | cell array of character vectors

Style to use when rendering the image, specified as a character vector or cell array of character vectors. The `StyleName` must be a valid entry in the `Layer.Details.Style.Name` field. If you request multiple layers, each with a different style, then `StyleName` must be a cell array of character vectors.

Example: `[A,R] = wmsread(layer(1), 'StyleName', 'style');`

Data Types: char | cell

Transparent — Pixel transparency

false (default) | true

Pixel transparency, specified as a logical value, `true` or `false`. When you set `Transparent` to `true`, pixel transparency is enabled, meaning all pixels not representing features or data values are set to a transparent value. When you set `Transparent` to `false`, non-data pixels are set to the value of the background color.

Example: `[A,R] = wmsread(layers(1), 'Transparent', true);`

Data Types: logical

BackgroundColor — Color used for background (nondata) pixels of the map

[255,255,255] (default) | three-element vector

Color used for background (nondata) pixels of the map, specified as a three-element vector.

Example: `[A,R] = wmsread(layers(1), 'BackgroundColor', [0,0,255]);`

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64`

Elevation — Desired elevation extent of the requested map

character vector

Desired elevation extent of the requested map, specified as a character vector. The layer must contain elevation data, which is indicated by the 'Name' field of the `Layer.Details.Dimension` structure. The 'Name' field must contain the value 'elevation'. The 'Extent' field of the `Layer.Details.Dimension` structure determines the permissible range of values for the parameter.

Example: `[A,R] = wmsread(layer(1), 'Elevation', 'test');`

Data Types: `char`

Time — Desired time extent of the requested map

character vector | numeric date number

Desired time extent of the requested map, specified as a character vector or numeric date number. The layer must contain data with a time extent, which is indicated by the 'Name' field of the `Layer.Details.Dimension` structure. The 'Name' field must contain the value 'time'. The 'Extent' field of the `Layer.Details.Dimension` structure determines the permissible range of values for the parameter. For more information about setting this parameter, see the `WMSMapRequest.Time` property reference page.

Example: `[A,R] = wmsread(layer(1), 'Time', 'June 15, 2015');`

Data Types: `double` | `char`

SampleDimension — Name of sample dimension

two-element cell array of character vectors

Name of dimension, specified as a two-element cell array of character vectors, other than 'time' or 'elevation' and its character vector value. The layer must contain data with a sample dimension extent, which is indicated by the 'Name' field of the

`Layer.Details.Dimension` structure. The 'Name' field must contain the value of the first element of 'SampleDimension'. The 'Extent' field of the `Layer.Details.Dimension` structure determines the permissible range of values for the second element of 'SampleDimension'.

Example: `[A,R] = wmsread(layer(1), 'SampleDimension', {'sample', 'test'});`

Data Types: cell

TimeoutInSeconds — Number of seconds to elapse before issuing a server time-out

60 (default) | scalar integer

Number of seconds to elapse before issuing a server time-out, specified as a scalar integer. If you set the value to 0, wms read ignores the time-out mechanism.

Example: `[A,R] = wmsread(layers(1), 'TimeoutInSeconds', 80);`

Data Types: single | double | int8 | int16 | int32 | int64 | uint8 | uint16 | uint32 | uint64

Output Arguments

A — Color or grayscale image

real, nonsparse, 2-D matrix

Color or grayscale image, returned as a real, nonsparse, 2-D matrix.

R — Geographic raster reference object

`map.rasterref.GeographicCellsReference` object

Geographic raster reference object, returned as a `map.rasterref.GeographicCellsReference` object. A raster referencing object ties the image A to the EPSG:4326 geographic coordinate system.

mapRequestURL — WMS GetMap request URL

character vector

WMS GetMap request URL, returned as a character vector.

Definitions

EPSG: 4326 Coordinate Reference System

The EPSG:4326 coordinate reference system is based on the WGS84 (1984 World Geodetic System) datum. Latitude and longitude are in degrees and longitude is referenced to the Greenwich Meridian.

Tips

- Establish an Internet connection to use `wmsread`. Periodically, the WMS server is unavailable. Retrieving the map can take several minutes. `wmsread` communicates with the server using a `WebMapServer` object representing a WMS server. The object acts as a proxy to a WMS server and resides physically on the client side. The object retrieves the map from the server. The object automatically times-out after 60 seconds if a connection is not made to the server.
- To specify a proxy server to connect to the Internet, select **File > Preferences > Web** and enter your proxy information. Use this feature if you have a firewall.
- `wmsread` supports reading data in WMS versions 1.0.0, 1.1.1, and 1.3.0. For version 1.3.0 only, the WMS specification states, "EPSG:4326 refers to WGS 84 geographic latitude, then longitude. That is, in this CRS the x-axis corresponds to latitude, and the y-axis to longitude." Most servers provide data in this manner; however, some servers conform to version 1.1.1, where the x-axis corresponds to longitude and the y-axis to latitude.

`wmsread` attempts to validate whether a server is conforming to the specification. It checks the EPSG:4326 bounding box, and if the `XLim` values exceeds the range of latitude, then the axes are swapped to conform to version 1.1.1 rather than 1.3.0. If `wmsread` does not detect that the `XLim` values exceed the range of latitude and you notice that the latitude and longitude limits are reversed, then you need to swap them. You can either modify the `bbox` parameters in the `mapRequestURL` or modify the `Latlim` and `Lonlim` parameter values, if permissible.

See Also

Functions

`wmsfind` | `wmsinfo` | `wmsupdate`

Objects

WMSCapabilities | WMSLayer | WMSMapRequest | WebMapServer

Introduced before R2006a

wmsupdate

Synchronize WMSLayer object with server

Syntax

```
[updatedLayers,index] = wmsupdate(layers)  
[...] = wmsupdate(layers,Name,Value, ...)
```

Description

[updatedLayers,index] = wmsupdate(layers) returns a Web Map Service (WMS) layer array with its properties synchronized with values from the server. The input layers contains only one unique ServerURL. Layers no longer available on the server are removed. The logical array index contains true for each available layer. Therefore, updatedLayers has the same size as layers(index). Except for deletion, updatedLayers preserves the same order of layers as layers.

[...] = wmsupdate(layers,Name,Value, ...) specifies parameter-value pairs that modify the request. Parameter names can be abbreviated and are case-insensitive.

The function accesses the Internet to update the properties. Periodically, the WMS server is unavailable. Updating the layer can take several minutes. The function times-out after 60 seconds if a connection is not made to the server.

Input Arguments

layers

Array of WMSLayer objects

Name-Value Pair Arguments

Specify optional comma-separated pairs of Name,Value arguments. Name is the argument name and Value is the corresponding value. Name must appear inside single

quotes (' '). You can specify several name and value pair arguments in any order as Name1,Value1,...,NameN,ValueN.

TimeoutInSeconds

Integer-valued, scalar double that indicates the number of seconds before a server times out. A value of 0 causes the time-out mechanism to be ignored.

Default: 60 seconds

AllowMultipleServers

Logical scalar that indicates whether the `layer` array may contain elements from multiple servers. Use caution when setting the value to `true`, since you are making a request to each unique server. Each request can take several minutes to finish.

Default: `false` (indicates the array must contain elements from the same server)

Output Arguments

updatedLayers

WMSLayer array with its properties synchronized with values from the server.

index


Logical array that contains `true` for each available layer.

Examples

Update the layers from the NASA Goddard Space Flight Center WMS SVS Image Server:

```
% Search the abstract field of the updated layers to find
% layers containing the term 'blue marble'. Read and display
% the first blue marble layer containing the term '512' and
% 'image' in its LayerTitle.
gsfc = wmsfind('svs.gsfc.nasa.gov', 'SearchField', 'serverurl');
gsfc = wmsupdate(gsfc);
blue_marble = refine(gsfc,'blue marble', 'SearchField', 'abstract');
queryStr = '*512*image';
```

```
layers = refine(blue_marble,queryStr);  
layer = layers(1);  
  
% Display the layer and abstract.  
[A, R] = wmsread(layer);  
figure  
worldmap world  
plabel off  
mlabel off  
geoshow(A,R)  
title(layer.LayerTitle)  
disp(layer.Abstract)
```



Courtesy NASA/Goddard Space Flight Center Scientific Visualization Studio

Update the properties of all the layers from NASA's Goddard Space Flight Center WMS servers:

```
nasa = wmsfind('gsfc.nasa.gov', 'SearchField', 'serverurl');  
nasa = wmsupdate(nasa, 'AllowMultipleServers', true);
```

Tips

- To specify a proxy server to connect to the Internet, click **Preferences** and, in the Preferences dialog box, select **Web**. Enter your proxy information. Use this feature if you have a firewall.

See Also

Functions

wmsfind | wmsinfo | wmsread

Objects

WMSLayer | WebMapServer

Introduced in R2009b

worldFileMatrix

Package: map.rasterref

Return world file parameters for transformation

Syntax

`W = worldFileMatrix(R)`

Description

`W = worldFileMatrix(R)` returns a 2-by-3 world file matrix from geographic or map raster `R`.

Examples

Create World File Matrix from a Planar Map Raster

Create a `MapCellsReference` raster reference object.

```
xWorldLimits = [207000 208000];
yWorldLimits = [912500 913000];
rasterSize = [10 20];
R = maprefcells(xWorldLimits,yWorldLimits,rasterSize,'ColumnsStartFrom','north')
```

`R =`

`MapCellsReference` with properties:

```
    XWorldLimits: [207000 208000]
    YWorldLimits: [912500 913000]
    RasterSize: [10 20]
    RasterInterpretation: 'cells'
    ColumnsStartFrom: 'north'
    RowsStartFrom: 'west'
    CellExtentInWorldX: 50
```

```
CellExtentInWorldY: 50
RasterExtentInWorldX: 1000
RasterExtentInWorldY: 500
  XIntrinsicLimits: [0.5 20.5]
  YIntrinsicLimits: [0.5 10.5]
TransformationType: 'rectilinear'
CoordinateSystemType: 'planar'
```

Compute the world file matrix.

```
W = worldFileMatrix(R)
```

```
W = 2×3
```

```
    50         0    207025
     0        -50    912975
```

Observe that $W(2,1)$ and $W(1,2)$ are 0. This value is expected since `R.TransformationType` is 'rectilinear'.

Input Arguments

R — Geographic or map raster

`GeographicCellsReference`, `GeographicPostingsReference`, `MapCellsReference`, or `MapPostingsReference` object

Geographic or map raster, specified as a `GeographicCellsReference`, `GeographicPostingsReference`, `MapCellsReference`, or `MapPostingsReference` object.

Output Arguments

W — World file matrix

2-by-3 numeric array

World file matrix, returned as a 2-by-3 numeric array. Each of the six elements in W matches one of the lines in a world file corresponding to the transformation defined by raster referencing object R .

Data Types: `double`

Definitions

World File Matrix

A world file matrix maps points in intrinsic coordinates to points in geographic or planar world coordinates.

Given a world file matrix W of the form:

$$W = \begin{bmatrix} A & B & C \\ D & E & F \end{bmatrix}$$

a point (x_i, y_i) maps to a point (x_w, y_w) in world coordinates according to:

$$\begin{aligned} x_w &= A \times (x_i - 1) + B \times (y_i - 1) + C \\ y_w &= D \times (x_i - 1) + E \times (y_i - 1) + F. \end{aligned}$$

More compactly:

$$\begin{bmatrix} x_w & y_w \end{bmatrix} = W \times \begin{bmatrix} (x_i - 1) & (y_i - 1) \end{bmatrix}.$$

Note Similar equations hold true for points (lat, lon) in geographic coordinates. However, the geographic coordinate ordering is switched. That is, x_w is substituted by lon , and y_w is substituted by lat .

The -1 s are needed to maintain the Mapping Toolbox convention for intrinsic coordinates, which is consistent with the 1-based indexing used throughout MATLAB.

W is stored in a world file with one term per line in column-major order: A, D, B, E, C, F . That is, a world file contains the elements of W in this order:

```
W(1,1)
W(2,1)
W(1,2)
W(2,2)
```

$W(1,3)$ $W(2,3)$

The previous expressions hold for both affine and rectilinear transformations of rasters. The values B , D , $W(2,1)$ and $W(1,2)$ are identically 0 whenever:

- R is a geographic raster, since longitude depends only on intrinsic x and latitude depends only on intrinsic y
- R is a map raster and $R.TransformationType$ is 'rectilinear'

See Also

Introduced in R2013b

worldFileMatrixToRefmat

Convert world file matrix to referencing matrix

Syntax

```
refmat = worldFileMatrixToRefmat(W)
```

Description

`refmat = worldFileMatrixToRefmat(W)` converts the 2-by-3 world file matrix `W` to a 3-by-2 referencing matrix `refmat`.

For a definition of a referencing matrix, see `makerefmat`.

For a definition of a world file matrix, see the `worldFileMatrix` method of the `map raster reference` and `geographic raster reference` classes.

See Also

`makerefmat` | `refmatToWorldFileMatrix`

Introduced in R2011a

worldfileread

Read world file and return referencing object or matrix

Syntax

```
R = worldfileread(worldFileName,coordinateSystemType,rasterSize)
refmat = worldfileread(worldFileName)
```

Description

`R = worldfileread(worldFileName,coordinateSystemType,rasterSize)` reads the world file, `worldFileName`, and constructs a spatial referencing object, `R`. The argument `coordinateSystemType` specifies the type of referencing object. `rasterSize` specifies the size of the image corresponding to the world file.

`refmat = worldfileread(worldFileName)` reads the world file, `worldFileName`, and constructs a 3-by-2 referencing matrix, `refmat`.

Examples

Read Image Referenced to Projected Coordinate System

Read an ortho image referenced to a projected coordinate system (Massachusetts State Plane Mainland).

```
filename = 'concord_ortho_w.tif';
[X, cmap] = imread(filename);
```

Derive worldfile name from image file name.

```
worldFileName = getworldfilename(filename);
```

Read the world file, returning a referencing object.

```
R = worldfileread(worldFileName, 'planar', size(X))
```

```
R =
  MapCellsReference with properties:
      XWorldLimits: [207000 209000]
      YWorldLimits: [911000 913000]
      RasterSize: [2000 2000]
  RasterInterpretation: 'cells'
      ColumnsStartFrom: 'north'
      RowsStartFrom: 'west'
      CellExtentInWorldX: 1
      CellExtentInWorldY: 1
  RasterExtentInWorldX: 2000
  RasterExtentInWorldY: 2000
      XIntrinsicLimits: [0.5 2000.5]
      YIntrinsicLimits: [0.5 2000.5]
  TransformationType: 'rectilinear'
  CoordinateSystemType: 'planar'
```

Read Image Referenced to Geographic Coordinate System

Read image reference to a geographic coordinate system.

```
filename = 'boston_ovr.jpg';
RGB = imread(filename);
```

Derive worldfile name from image file name,

```
worldFileName = getworldfilename(filename);
```

Read world file, returning a referencing object.

```
R = worldfileread(worldFileName, 'geographic', size(RGB))
```

```
R =
  GeographicCellsReference with properties:
      LatitudeLimits: [42.3052018188767 42.4165064733949]
      LongitudeLimits: [-71.1308390797572 -70.9898400731705]
      RasterSize: [769 722]
  RasterInterpretation: 'cells'
```



```

ColumnsStartFrom: 'north'
RowsStartFrom: 'west'
CellExtentInLatitude: 0.000144739472715501
CellExtentInLongitude: 0.000195289482807142
RasterExtentInLatitude: 0.11130465451822
RasterExtentInLongitude: 0.140999006586757
XIntrinsicLimits: [0.5 722.5]
YIntrinsicLimits: [0.5 769.5]
CoordinateSystemType: 'geographic'
AngleUnit: 'degree'

```

Input Arguments

worldFileName — Name of world file

character vector

Name of world file, specified as a character vector.

Example: worldFileName = getworldfilename(filename);

Data Types: char

coordinateSystemType — Type of referencing object

'planar' | 'geographic'

Type of referencing object, specified as one of the following:

| Value | Description |
|--------------|----------------------------------|
| 'geographic' | Latitude-longitude systems |
| 'planar' | Projected map coordinate systems |

Example: R = worldfileread(worldFileName, 'geographic', size(RGB));

Data Types: char

rasterSize — Size of the image corresponding to the world file

Vector of image dimensions

Size of the image corresponding to the world file, specified as a vector of image dimensions. For example, for a two-dimensional image, the vector has the form [width height].

Example: `size(I)`;

Data Types: `double`

Output Arguments

R — Spatial referencing object

raster reference object

Spatial referencing object, returned as a raster reference object.

refmat — Referencing matrix

3-by-2 matrix

Referencing matrix, returned as a 3-by-2 `double` matrix.

See Also

`getworldfilename` | `map2pix` | `pix2map` | `worldfilewrite`

Introduced before R2006a

worldfilewrite

Write world file from referencing object or matrix

Syntax

```
worldfilewrite(R, worldfilename)
```

Description

`worldfilewrite(R, worldfilename)` calculates the world file entries corresponding to referencing object or matrix `R` and writes them into the file `worldfilename`. The argument `R` can be a map raster reference object, a geographic raster reference object, or a 3-by-2 referencing matrix.

Examples

Write out the information from a referencing object for the image file `concord_ortho_w.tif`

```
info = imfinfo('concord_ortho_w.tif');  
R = worldfileread('concord_ortho_w.tfw', ...  
    'planar', [info.Height info.Width])  
worldfilewrite(R, 'concord_ortho_w_test.tfw');  
type concord_ortho_w_test.tfw
```

See Also

[getworldfilename](#) | [map2pix](#) | [pix2map](#) | [worldfileread](#)

Introduced before R2006a

worldmap

Construct map axes for given region of world

Syntax

```
worldmap region  
worldmap(region)  
worldmap  
worldmap(latlim,lonlim)  
worldmap(Z,R)  
h = worldmap( ___ )
```

Description

`worldmap region` or `worldmap(region)` sets up an empty map axes with projection and limits suitable to the part of the world specified in `region`.

`worldmap` with no arguments presents a menu from which you can select the name of a single continent, country, island, or region.

`worldmap(latlim,lonlim)` allows you to define a custom geographic region in terms of its latitude and longitude limits in degrees.

`worldmap(Z,R)` derives the map limits from the extent of a regular data grid, `Z`, georeferenced by `R`.


`h = worldmap(___)` returns the handle of the map axes.

Examples

Set up World Map and Draw Coastlines

Set up a world map and draw coarse coastlines.

```
worldmap('World')  
load coastlines  
plotm(coastlat,coastlon)
```




Set up World Map with Land Areas, Lakes, and Other Landmarks

Set up a world map with land areas, major lakes and rivers, and cities and populated places.

```
ax = worldmap('World');  
setm(ax, 'Origin', [0 180 0])
```

```
land = shaperead('landareas', 'UseGeoCoords', true);
geoshow(ax, land, 'FaceColor', [0.5 0.7 0.5])
lakes = shaperead('worldlakes', 'UseGeoCoords', true);
geoshow(lakes, 'FaceColor', 'blue')
rivers = shaperead('worldrivers', 'UseGeoCoords', true);
geoshow(rivers, 'Color', 'blue')
cities = shaperead('worldcities', 'UseGeoCoords', true);
geoshow(cities, 'Marker', '.', 'Color', 'red')
```




Draw Map of Antarctica

Draw a map of Antarctica, using the `worldmap` function.

```

worldmap('antarctica')
antarctica = shaperead('landareas', 'UseGeoCoords', true, ...
    'Selector',{@(name) strcmp(name,'Antarctica'), 'Name'});
patchm(antarctica.Lat, antarctica.Lon, [0.5 1 0.5])

```



Draw a map of Africa and India with Major Cities


Draw a map of Africa and India with major cities and populated areas.

```

worldmap({'Africa', 'India'})
land = shaperead('landareas.shp', 'UseGeoCoords', true);
geoshow(land, 'FaceColor', [0.15 0.5 0.15])

```


```
cities = shaperead('worldcities', 'UseGeoCoords', true);  
geoshow(cities, 'Marker', '.', 'Color', 'red')
```



Map the Geoid over South America and Central Pacific

Make a map of the geoid over South America and the central Pacific.


```
worldmap([-50 50],[160 -30])  
load geoid  
geoshow(geoid, geoidrefvec, 'DisplayType', 'texturemap');  
load coastlines  
geoshow(coastlat,coastlon)
```

Draw Map of Terrain Elevations in Korea

Draw a map of terrain elevations in Korea.

```
load korea
h = worldmap(map, refvec);
set(h, 'Visible', 'off')
geoshow(h, map, refvec, 'DisplayType', 'texturemap')
demcmap(map)
```




Map the United States of America Coloring State Polygons

Make a map of the United States of America, coloring state polygons.

```
ax = worldmap('USA');  
load coastlines  
geoshow(ax, coastlat, coastlon,...  
        'DisplayType', 'polygon', 'FaceColor', [.45 .60 .30])  
states = shaperead('usastatelo', 'UseGeoCoords', true);  
faceColors = makesymbolspec('Polygon',...  
        {'INDEX', [1 numel(states)], 'FaceColor', ...
```

```
polcmap(numel(states)); % NOTE - colors are random  
geoshow(ax, states, 'DisplayType', 'polygon', ...  
    'SymbolSpec', faceColors)
```



Input Arguments

region — Region to display

'World' | 'North Pole' | 'South Pole' | 'Pacific' | character vector | string scalar | string array | cell array of character vectors

Region to display, specified as a string scalar, string array, character vector, or cell array of character vectors. Permissible values include names of continents, countries, and islands as well as 'World', 'North Pole', 'South Pole', and 'Pacific'.

Example: {'Africa', 'India'}

latlim — Latitude limits

two-element vector

Latitude limits, specified as a two-element vector of the form [southern_limit northern_limit].

lonlim — Longitude limits

two-element vector

Longitude limits, specified as a two-element vector of the form [western_limit eastern_limit].

Z — Data grid

M-by-N array

Data grid, specified as an M-by-N array. Z is a regular data grid associated with a geographic reference R.

R — Geographic reference

geographic raster reference object | vector | matrix

Geographic reference, specified as one of the following.

| Type | Description |
|------------------------------------|---|
| Geographic raster reference object | GeographicCellsReference or GeographicPostingsReference geographic raster reference object. The RasterSize property must be consistent with the size of the data grid, size(Z). |
| Vector | 1-by-3 numeric vector with elements: [cells/degree northern_latitude_limit western_longitude_limit] |

| Type | Description |
|--------|--|
| Matrix | <p>3-by-2 numeric matrix that transforms raster row and column indices to or from geographic coordinates according to:</p> $[\text{lon } \text{lat}] = [\text{row } \text{col } 1] * R$ <p>R defines a (non-rotational, non-skewed) relationship in which each column of the data grid falls along a meridian and each row falls along a parallel.</p> |

For more information about referencing vectors and matrices, see “Georeferenced Raster Data”.

Output Arguments

h — Handle of the map axes

handle object

Handle of the map axes, returned as a handle object.

Tips

- All axes created with `worldmap` are initialized with a spherical Earth model having a radius of 6,371,000 meters.
- `worldmap` uses `tightmap` to adjust the axes limits around the map. If you change the projection, or just want more white space around the map frame, use `tightmap` again or `auto axis`.

See Also

`axesm` | `framem` | `geoshow` | `gridm` | `mlabel` | `plabel` | `tightmap` | `usamap`

Introduced before R2006a

worldToDiscrete

Package: map.rasterref

Transform planar world to discrete coordinates

Syntax

```
[I,J] = worldToDiscrete(R,xWorld,yWorld)
```

Description

[I,J] = worldToDiscrete(R,xWorld,yWorld) returns the indices corresponding to world coordinates xWorld and yWorld in map raster R. If R.RasterInterpretation is:

- 'cells', then I and J are the row and column subscripts of the raster cells (or image pixels)
- 'postings', then I and J refer to the nearest sample point (posting)

Input Arguments

R — Map raster

MapCellsReference or MapPostingsReference object

Map raster, specified as a MapCellsReference or MapPostingsReference object.

xWorld — x-coordinates in the world coordinate system

numeric array

x-coordinates in the world coordinate system, specified as a numeric array.

Data Types: single | double

yWorld — y-coordinates in the world coordinate system

numeric array

y -coordinates in the world coordinate system, specified as a numeric array. `yWorld` is the same size as `xWorld`.

Data Types: `single` | `double`

Output Arguments

I — World x -coordinate indices

array of integers

World x -coordinate indices, returned as an array of integers. `I` is the same size as `xWorld`.

For an m -by- n raster, $1 \leq I \leq m$, except for points $(xWorld(k), yWorld(k))$ that fall outside the bounds of the raster as defined by the function `contains`. In this case `I(k)` and `J(k)` are `NaN`.

Data Types: `double`

J — World y -coordinate indices

array of integers

World y -coordinate indices, returned as an array of integers. `J` is the same size as `yWorld`.

For an m -by- n raster, $1 \leq I \leq m$, except for points $(xWorld(k), yWorld(k))$ that fall outside the bounds of the raster as defined by the function `contains`. In this case `I(k)` and `J(k)` are `NaN`.

Data Types: `double`

See Also

`contains` | `geographicToDiscrete` | `worldToIntrinsic`

Introduced in R2013b

worldToIntrinsic

Package: map.rasterref

Transform planar world to intrinsic coordinates

Syntax

```
[xIntrinsic,yIntrinsic] = worldToIntrinsic(R,xWorld,yWorld)
```

Description

[xIntrinsic,yIntrinsic] = worldToIntrinsic(R,xWorld,yWorld) returns the intrinsic coordinates corresponding to planar world coordinates (xWorld, yWorld) in map raster R. If a point is outside the bounds of R, then worldToIntrinsic extrapolates the xIntrinsic and yIntrinsic coordinates.

Input Arguments

R — Map raster

MapCellsReference or MapPostingsReference object

Map raster, specified as a MapCellsReference or MapPostingsReference object.

xWorld — x-coordinates in the world coordinate system

numeric array

x-coordinates in the world coordinate system, specified as a numeric array. xWorld coordinates can be outside the bounds of the raster R.

Data Types: single | double

yWorld — y-coordinates in the world coordinate system

numeric array

y-coordinates in the world coordinate system, specified as a numeric array. yWorld is the same size as xWorld. yWorld coordinates can be outside the bounds of the raster R.

Data Types: `single` | `double`

Output Arguments

xIntrinsic — *x*-coordinates in the intrinsic coordinate system

numeric array

x-coordinates in the intrinsic coordinate system, returned as a numeric array. `xIntrinsic` is the same size as `xWorld`.

When `xWorld(k)` is outside the bounds of raster `R`, `xIntrinsic(k)` is extrapolated in the intrinsic coordinate system.

Data Types: `double`

yIntrinsic — *y*-coordinates in the intrinsic coordinate system

numeric array

y-coordinates in the intrinsic coordinate system, returned as a numeric array. `yIntrinsic` is the same size as `xWorld`.

When `yWorld(k)` outside the bounds of raster `R`, `yIntrinsic(k)` is extrapolated in the intrinsic coordinate system.

Data Types: `double`

See Also

`geographicToIntrinsic` | `intrinsicToWorld` | `worldToDiscrete`

Introduced in R2013b

wrapTo180

Wrap angle in degrees to [-180 180]

Syntax

```
lonWrapped = wrapTo180(lon)
```

Description

`lonWrapped = wrapTo180(lon)` wraps angles in `lon`, in degrees, to the interval [-180, 180] such that 180 maps to 180 and -180 maps to -180. In general, odd, positive multiples of 180 map to 180 and odd, negative multiples of 180 map to -180.

Examples

Wrap Longitudes to 180 Degrees

Specify a short list of longitudes to wrap.

```
lon = [-400 -190 -180 -175 175 180 190 380];
```

Wrap the longitudes to the range [-180, 180] degrees.

```
lonWrapped = wrapTo180(lon)
```

```
lonWrapped = 1×8
```


```
   -40    170   -180   -175    175    180   -170    20
```

Specify a second list of longitudes that are sampled over a large range of angles. Wrap the longitudes.

```
lon2 = -720:720;  
lon2Wrapped = wrapTo180(lon2);
```

Plot the wrapped longitudes. The wrapped longitudes stay in the range [-180, 180] degrees.

```
plot(lon2, lon2Wrapped)  
xlabel("Longitude (degrees)")  
ylabel("Wrapped Longitude (degrees)")  
grid on
```



Input Arguments

lon — Angles
numeric vector

Angles, specified as a numeric vector.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64` | `logical`

Output Arguments

LonWrapped — Wrapped angles

numeric vector

Wrapped angles, specified as a numeric vector with values in the range $[-180, 180]$.

See Also

`wrapTo2Pi` | `wrapTo360` | `wrapToPi`

Introduced in R2007b

wrapTo360

Wrap angle in degrees to [0 360]

Syntax

```
lonWrapped = wrapTo360(lon)
```

Description

`lonWrapped = wrapTo360(lon)` wraps angles in `lon`, in degrees, to the interval [0, 360] such that 0 maps to 0 and 360 maps to 360. In general, positive multiples of 360 map to 360 and negative multiples of 360 map to zero.

Examples

Wrap Longitudes to 360 Degrees

Specify a short list of longitudes to wrap.

```
lon = [-720 -400 -360 -355 350 360 370 720];
```

Wrap the longitudes to the range [0, 360] degrees.

```
lonWrapped = wrapTo360(lon)
```

```
lonWrapped = 1×8
```


```
0    320    0     5    350    360    10    360
```

Specify a second list of longitudes that are sampled over a large range of angles. Wrap the longitudes.

```
lon2 = -1000:1000;  
lon2Wrapped = wrapTo360(lon2);
```

Plot the wrapped longitudes. The wrapped longitudes stay in the range [0, 360] degrees.

```
plot(lon2, lon2Wrapped)  
xlabel("Longitude (degrees)")  
ylabel("Wrapped Longitude (degrees)")  
grid on
```



Input Arguments

lon — Angles
numeric vector

Angles, specified as a numeric vector.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64` | `logical`

Output Arguments

LonWrapped — Wrapped angles

numeric vector

Wrapped angles, specified as a numeric vector with values in the range [0, 360].

See Also

`wrapTo2Pi` | `wrapTo360` | `wrapToPi`

Introduced in R2007b

wrapTo2Pi

Wrap angle in radians to $[0, 2\pi]$

Syntax

```
lambdaWrapped = wrapTo2Pi(lambda)
```

Description

`lambdaWrapped = wrapTo2Pi(lambda)` wraps angles in `lambda`, in radians, to the interval $[0, 2\pi]$ such that 0 maps to 0 and 2π maps to 2π . In general, positive multiples of 2π map to 2π and negative multiples of 2π map to 0.

Examples

Wrap Angles to 2Pi Radians

Specify a short list of angles to wrap.

```
lambda = [-2*pi -pi-0.1 -pi -2.8 3.1 pi pi+1 2*pi];
```

Wrap the angles to the range $[0, 2\pi]$ radians.

```
lambdaWrapped = wrapTo2Pi(lambda)
```

```
lambdaWrapped = 1x8
```


```
0      3.0416      3.1416      3.4832      3.1000      3.1416      4.1416      6.2832 ...
```

Specify a second list of angles, and wrap them.

```
lambda2 = -10:0.1:10;  
lambda2Wrapped = wrapTo2Pi(lambda2);
```


Plot the wrapped angles. The wrapped angles stay in the range $[0, 2\pi]$ radians.

```
plot(lambda2, lambda2Wrapped)  
xlabel("Angle (radians)")  
ylabel("Wrapped Angle (radians)")  
grid on
```



Input Arguments

lambda — Angles

numeric vector

Angles, specified as a numeric vector.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64` | `logical`

Output Arguments

LambdaWrapped — Wrapped angles

numeric vector

Wrapped angles, specified as a numeric vector with values in the range $[0, 2\pi]$.

See Also

`wrapTo180` | `wrapTo360` | `wrapToPi`

Introduced in R2007b

wrapToPi

Wrap angle in radians to $[-\pi, \pi]$

Syntax

```
lambdaWrapped = wrapToPi(lambda)
```

Description

`lambdaWrapped = wrapToPi(lambda)` wraps angles in `lambda`, in radians, to the interval $[-\pi, \pi]$ such that π maps to π and $-\pi$ maps to $-\pi$. In general, odd, positive multiples of π map to π and odd, negative multiples of π map to $-\pi$.

Examples

Wrap Angles to Pi Radians

Specify a short list of angles to wrap.

```
lambda = [-2*pi -pi-0.1 -pi -2.8 3.1 pi pi+1 2*pi];
```

Wrap the angles to the range $[-\pi, \pi]$ radians.

```
lambdaWrapped = wrapToPi(lambda)
```

```
lambdaWrapped = 1x8
```


```
0    3.0416   -3.1416   -2.8000    3.1000    3.1416   -2.1416    0 ...
```

Specify a second list of angles, and wrap them.

```
lambda2 = -10:0.1:10;
lambda2Wrapped = wrapToPi(lambda2);
```

Plot the wrapped angles. The wrapped angles stay in the range $[-\pi, \pi]$ radians.

```
plot(lambda2, lambda2Wrapped)  
xlabel("Angle (radians)")  
ylabel("Wrapped Angle (radians)")  
grid on
```



Input Arguments

lambda — Angles

numeric vector

Angles, specified as a numeric vector.

Data Types: `single` | `double` | `int8` | `int16` | `int32` | `int64` | `uint8` | `uint16` | `uint32` | `uint64` | `logical`

Output Arguments

LambdaWrapped — Wrapped angles

numeric vector

Wrapped angles, specified as a numeric vector with values in the range $[-\pi, \pi]$.

See Also

`wrapTo180` | `wrapTo2Pi` | `wrapTo360`

Introduced in R2007b

zdatam

Adjust z-plane of displayed map objects

Syntax

```
zdatam  
zdatam(hndl)  
zdatam('str')  
zdatam(hndl,zdata)  
zdatam('str',zdata)
```

Description

`zdatam` displays a GUI for selecting an object from the current axes and modifying its `ZData` property.

`zdatam(hndl)` and `zdatam('str')` display a GUI to modify the `ZData` of the object(s) specified by the input. `str` is any character vectors recognized by `handlem`.

`zdatam(hndl,zdata)` alters the *z*-plane position of displayed map objects designated by the MATLAB graphics handle `hndl`. The *z*-plane position may be the *Z* position in the case of text objects, or the `ZData` property in the case of other graphic objects. The function behaves as follows:

- If `hndl` is an `hggroup` handle, the `ZData` property of the children in the `hggroup` are altered.
- If the handle is scalar, then `ZData` can be either a scalar (*z*-plane definition), or a matrix of appropriate dimension for the displayed object.
- If `hndl` is a vector, then `ZData` can be a scalar or a vector of the same dimension as `hndl`.
- If `ZData` is a scalar, then all objects in `hndl` are drawn on the `ZData` *z*-plane.
- If `ZData` is a vector, then each object in `hndl` is drawn on the plane defined by the corresponding `ZData` element.

- If `ZData` is omitted, then a modal dialog box prompts for the `ZData` entry.

`zdatam('str', zdata)` identifies the objects by the input `str`, where `str` is any of the character vectors recognized by `handlem`, and uses `zdata` as described above to update their `ZData` property.

This function adjusts the z-plane position of selected graphics objects. It accomplishes this by setting the objects' `ZData` properties to the appropriate values.

See Also

`handlem` | `setm`

Introduced before R2006a

zero22pi

Wrap longitudes to [0 360] degree interval

Note The `zero22pi` function has been replaced by `wrapTo360` and `wrapTo2Pi`.

Syntax

```
newlon = zero22pi(lon)
newlon = zero22pi(lon,angleunits)
```

Description

`newlon = zero22pi(lon)` *wraps* the input angle `lon` in degrees to the 0 to 360 degree range.

`newlon = zero22pi(lon,angleunits)` works in the units defined by *angleunits*, which can be either 'degrees' or 'radians'. *angleunits* can be abbreviated and is case-insensitive.

Examples

```
zero22pi(567.5)
```

```
ans =
    207.5
```

```
zero22pi(-567.5)
```

```
ans =
    152.5
```

```
zero22pi(-7.5,'radian')
```



```
ans =  
    5.0664
```

See Also

`wrapTo2Pi` | `wrapTo360`

Introduced before R2006a

zerom

Construct regular data grid of 0s

Note `zerom` is not recommended and may be removed in a future release. Instead, use `georefcells` to construct a geographic raster reference object and then use `zeros` to initialize a data grid of the appropriate size:

```
R = georefcells(latlim,lonlim,1/scale,1/scale);  
Z = zeros(R.RasterSize);
```

Syntax

```
[Z,refvec] = zerom(latlim,lonlim,scale)
```

Description

`[Z,refvec] = zerom(latlim,lonlim,scale)` returns a full regular data grid consisting entirely of 0s and a three-element referencing vector for the returned Z. The two-element vectors `latlim` and `lonlim` define the latitude and longitude limits of the geographic region. They should be of the form `[south north]` and `[west east]`, respectively. The scalar `scale` specifies the number of rows and columns per degree of latitude and longitude.

Examples

```
[Z,refvec] = zerom([46,51],[-79,-75],1)
```

```
Z =  
    0    0    0    0  
    0    0    0    0  
    0    0    0    0  
    0    0    0    0  
    0    0    0    0
```

```
refvec =  
  1    51   -79
```

See Also

limitm | nanm | onem | sizem | spzerom

Introduced before R2006a

axesmui

Define map axes and modify map projection and display properties

Activation

| Command Line | Maptool | Map Display |
|--|--------------------------------|--------------------------|
| axesmui <code>c = axesmui(...)</code> | Display > Projection | extend-click map display |

Description

axesmui activates a Projection Control dialog box for the current map axes. The dialog box allows map projection definition and property modification.

c is an optional output argument that indicates whether the Projection Control dialog box was closed by the cancel button. `c = 1` if the cancel button is pushed. Otherwise, `c = 0`.

Extend-clicking a map display brings up the Projection Control dialog box for that map axes.

Controls

The screenshot shows the 'Projection Control' dialog box. The 'Map Projection' dropdown is set to 'Azim: Globe'. The 'Geoid' section has '1' and '0' in its input fields and 'unit sphere' in the dropdown. 'Angle Units' is set to 'degrees'. The 'Map Limits' and 'Frame Limits' sections have 'Latitude' input fields with values '-90' and '90', and 'Longitude' input fields with values '-180' and '180'. The 'Map Origin' section has 'Lat and Long' input fields with values '0' and '0', and an 'Orientation' input field with value '0'. The 'Cartesian Origin' section has 'False E and N' input fields with values '0' and '0', and a 'Scalefactor' input field with value '1'. The 'Parallels' dropdown is set to 'None' and the 'Aspect' dropdown is set to 'normal'. At the bottom, there are buttons for 'Frame', 'Grid', 'Labels', 'Fill in', 'Reset', 'Apply', 'Help', and 'Cancel'.

The **Map Projection** pull-down menu is used to select a map projection. The projections are listed by type, and each is preceded by a four-letter type indicator:

Cyln = Cylindrical
 Pcyl = Pseudocylindrical
 Coni = Conic
 Poly = Polyconic
 Pcon = Pseudoconic
 Azim = Azimuthal
 Mazi = Modified Azimuthal
 Pazi = Pseudoazimuthal

The **Zone** button and edit box are used to specify the UTM or UPS zone. For non-UTM and UPS projections, the two are disabled.

The **Geoid** edit boxes and pull-down menu are used to specify the geoid. Units must be in meters for the UTM and UPS projections, since this is the standard unit for the two projections. For non-UTM and UPS projections, the geoid unit can be anything, bearing in mind that the resulting projected data will be in the same units as the geoid.

The **Angle Units** pull-down menu is used to specify the angle units used on the map projection. All angle entries corresponding to the current map projection must be entered in these units. Current angle entries are automatically updated when new angle units are selected.

The **Map Limits** edit boxes are used to specify the extent of the map data in geographic coordinates. The **Latitude** edit boxes contain the southern and northern limits of the map. The **Longitude** edit boxes contain the western and eastern limits of the map. The map limits establish the extent of the meridian and parallel grid lines, regardless of the display settings (see grid settings). Map limits are always in geographic coordinates, regardless of the map origin and orientation setting. In the normal aspect, the map display is trimmed to the minimum of the map and frame limits.

The **Frame Limits** edit boxes are used to specify the location of the map frame, measured from the center of the map projection in the base coordinate system. The **Latitude** edit boxes contain the southern and northern frame edge locations. The **Longitude** edit boxes contain the western and eastern frame edge locations. Displayed map data are trimmed at the frame limits. For azimuthal map projections, the latitude limits should be set to `-inf` and the desired trim distance from the map origin. In the normal aspect, the map display is trimmed to the minimum of the map and frame limits.

The **Map Origin** edit boxes are used to specify the origin and aspect angle of the map projection. The **Lat** and **Long** boxes specify the map origin in geographic coordinates. This is the point that is placed in the center of the projection. If either box is left blank, 0 degrees is used. The **Orientation** box specifies the azimuth angle of the North Pole relative to the map origin. Azimuth is measured clockwise from the top of the projection. If the **Orientation** box is disabled, then the selected map projection requires a fixed orientation. See the *Mapping Toolbox User's Guide* for a complete description of the map origin.

The **Cartesian Origin** edit boxes are used to specify the x-y offset, along with a desired scale factor of the map projection. The **False E and N** boxes specify the false easting and northing in Cartesian coordinates. These must be in the same units as the geoid. The **Scalefactor** box specifies the scale factor used in the map projection calculations.

The **Parallels** edit boxes specify the standard parallels of the selected map projection. A particular map projection may have one or two standard parallels. If the edit boxes are disabled, then the selected projection has no standard parallels or the standard parallels are fixed.

The **Aspect** pull-down menu is used to select a normal or transverse display aspect. When the aspect is normal, *north* (on the base projection) is up, and the map is displayed in a *portrait* setting. In a transverse aspect, north (in the base projection) is to the right, and the map is displayed in a *landscape* setting. This property does not control the map projection aspect. The projection aspect is determined by the map **Origin** property).

The **Frame** button brings up the Map Frame Properties dialog box, which allows the map frame settings to be modified.

The **Grid** button brings up the Map Grid Properties dialog box, which allows the map grid settings to be modified.

The **Labels** button brings up the Map Label Properties dialog box, which allows the parallel and meridian label settings to be modified.

The **Fill in** button is used to compute projection and display settings based on any currently specified map parameters. Only settings that are left blank are affected when this button is pushed.

The **Reset** button is used to reset the default projection properties and display settings of the current map. Default display settings include frame, grid, and label properties set to 'off'.


The **Apply** button is used to apply the projection and display settings to the current map, which results in the map being reprojected.

The **Help** button is used to bring up online help text for each control on the Projection Control dialog box.

The **Cancel** button disregards any modified projection or display settings and closes the Projection Control dialog box.

Map Frame Properties Dialog Box

This dialog box allows modification of the map frame settings. It is accessed via the **Frame** button on the Projection Control dialog box.



The **Frame** selection buttons determine whether the map frame is visible.

The **Face Color** pull-down menu is used to select the background color of the map frame. Selecting **none** results in a transparent frame background, i.e., the same as the axes color. Selecting **custom** allows a custom RGB triple to be defined for the background color.

The **Edge Color** pull-down menu is used to select the color of the frame edge. Selecting **none** hides the frame edge. Selecting **custom** allows a custom RGB triple to be defined for the edge color.

The **Edge Width** edit box is used to enter the line width of the frame edge, in points.


The **Points per Edge** edit box is used to enter the number of points used to display each edge of the map frame.

The **Accept** button accepts any modifications made to the map frame properties and returns to the Projection Control dialog box. Changes are applied to the current map only when the **Apply** button on the Projection Control dialog box is pushed.

The **Cancel** button disregards any modifications to the map frame properties and returns to the Projection Control dialog box.

Map Grid Properties Dialog Box

This dialog box allows modification of the map frame settings. It is accessed via the **Grid** button on the Projection Control dialog box.



The **Grid** selection buttons determine whether the map grid is visible.

The **Color** pull-down menu is used to select the color of the map grid lines. Selecting custom allows a custom RGB triple to be defined for the grid line color.

The **Style** pull-down menu is used to select the line style of the map grid lines.

The **Line Width** edit box is used to enter the width of the map grid lines, in points.

The **Grid Altitude** edit box is used to enter z-axis location of the map grid. This property can be used to place some mapped objects above or below the map grid. The default map grid altitude is `inf`, which places the grid above all other mapped objects.


The **Meridian and Parallel Settings** button brings up the **Meridian and Parallel Properties** dialog box, which allows the properties of the meridian and parallel grid lines to be modified.

The **Accept** button accepts any modifications made to the map grid properties and returns to the Projection Control dialog box. Changes are applied to the current map only when the **Apply** button on the Projection Control dialog box is pushed.

The **Cancel** button disregards any modifications to the map grid properties and returns to the Projection Control dialog box.

Meridian and Parallel Properties Dialog Box

This dialog box is used to modify the settings for meridian and parallel grid lines. It is accessed via the **Meridian and Parallel Settings** button on the Map Grid Properties dialog box.



The **Meridians** selection buttons determine whether the meridian grid lines are visible when the map grid is turned on.

The **Longitude Location(s)** edit box is used to specify which meridians are to be displayed if the meridian lines are turned on. If a scalar interval value is entered,

meridian lines are displayed at that interval, starting from the Prime Meridian and proceeding in east and west directions. If a vector of values is entered, meridian lines are displayed at locations given by each element of the vector.

The **Latitude Limits** edit box is used to specify the latitude limits beyond which meridian lines do not extend. If this property is left empty, all meridian lines extend to the map latitude limits (specified by the Latitude Map Limits entry on the **Projection Control** dialog box). This entry must be a two-element vector enclosed in brackets.

The **Longitude Exceptions** edit box is used to enter specific meridians of the displayed grid that are to extend beyond the latitude limits, to the map limits. This entry is a vector of longitude values.

The **Parallels** selection buttons determine whether the parallel grid lines are visible when the map grid is turned on.

The **Latitude Location(s)** edit box is used to specify which parallels are to be displayed if the parallel lines are turned on. If a scalar interval value is entered, parallel lines are displayed at that interval, starting from the Equator and proceeding in north and south directions. If a vector of values is entered, parallel lines are displayed at locations given by each element of the vector.

The **Longitude Limits** edit box is used to specify the longitude limits beyond which parallel lines do not extend. If this property is left empty, all parallel lines extend to the map longitude limits (specified by the Longitude Map Limits entry on the **Projection Control** dialog box). This entry must be a two-element vector enclosed in brackets.

The **Latitude Exceptions** edit box is used to enter specific parallels of the displayed grid that are to extend beyond the longitude limits, to the map limits. This entry is a vector of latitude values.


The **Points per Line** edit boxes are used to enter the number of points used to plot each meridian and each parallel grid line. The default value is 100 points.

The **Accept** button accepts any modifications that have been made to the meridian and parallel grid line properties and return to the Map Grid Properties dialog box. Changes are applied to the current map only when the **Apply** button on the Projection Control dialog box is pushed.

The **Cancel** button disregards any modifications to the meridian and parallel grid lines and returns to the Map Grid Properties dialog box.

Map Label Properties Dialog Box

This dialog box is used to modify the settings of the meridian and parallel labels. It is accessed via the **Label** button on the Projection Control dialog box.



The **Meridian** and **Parallel** selection buttons determine whether the meridian and parallel labels are visible.

The **Format** pull-down menu is used to specify the format of the grid labels. If **compass** is selected, meridian labels are appended with E for east and W for west, and parallel labels are appended with N for north and S for south. If **signed** is chosen, meridian labels are prefixed with + for east and - for west, and parallel labels are prefixed with + for north and - for south. If **none** is selected, western meridian labels and southern parallel labels are prefixed by -, but no symbol precedes eastern meridian labels and northern parallel labels.

The label **Units** pull-down menu is used to specify the angle units used to display the parallel and meridian labels. These units, used for display purposes only, need not be the same as the angle units of the map projection.

The **Font** edit box is used to specify the character font used to display the parallel and meridian labels. If the font specified does not exist on the computer, the default of Helvetica is used. Pressing the **Font** button previews the selected font.

The font **Size** edit box is used to enter an integer value that specifies the font size of the parallel and meridian labels. This value must be in the units specified by the font **Units** pull-down menu.

The font **Color** pull-down menu is used to select the color of the parallel and meridian labels. Selecting **custom** allows a custom RGB triple to be defined for the labels.

The font **Weight** pull-down menu is used to specify the character weight of the parallel and meridian labels.

The font **Units** pull-down menu is used to specify the units used to interpret the font size entry. When set to **normalized**, the value entered in the **Size** edit box is interpreted as a fraction of the height of the axes. For example, a normalized font size of 0.1 sets the label text to a height of one tenth of the axes height.

The font **Angle** pull-down menu is used to select the character slant of the parallel and meridian labels. **normal** specifies nonitalic font. **italic** and **oblique** specify italic font.


The **Meridian and Parallel Settings** button brings up the Meridian and Parallel Label Properties dialog box, which allows modification of properties specific to the meridian and parallel grid labels.

The **Accept** button accepts any modifications that have been made to the map label properties and returns to the Projection Control dialog box. Changes are applied to the current map only when the **Apply** button on the Projection Control dialog box is pushed.

The **Cancel** button disregards any modifications to the map labels and returns to the **Projection Control** dialog box.

Meridian and Parallel Label Properties Dialog Box

This dialog box is used to modify properties specific to the meridian and parallel grid labels. It is accessed via the **Meridian and Parallel Settings** button on the Map Label Properties dialog box.



The **Longitude Location(s)** edit box is used to specify which meridians are to be labeled. Meridian labels need not coincide with displayed meridian grid lines. If a scalar interval value is entered, labels are displayed at that interval, starting from the Prime Meridian and proceeding in east and west directions. If a vector of values is entered, labels are displayed at longitude locations given by each element of the vector.

The **Display Parallel** pull-down menu and edit box are used to specify the latitude location of the meridian labels. If a scalar latitude value is provided in the edit box, the meridian labels are placed at that parallel. Alternatively, the pull-down menu can be used to select a latitude location. If **north** is chosen, meridian labels are placed at the maximum map latitude limit. If **south** is chosen, meridian labels are placed at the minimum map latitude limit.

The **Latitude Location(s)** edit box is used to specify which parallels are to be labeled. Parallel labels need not coincide with displayed parallel grid lines. If a scalar interval value is entered, labels are displayed at that interval, starting from the Equator and proceeding in north and south directions. If a vector of values is entered, labels are displayed at latitude locations given by each element of the vector.

The **Display Meridian** pull-down menu and edit box are used to specify the longitude location of the parallel labels. If a scalar longitude value is provided in the edit box, the parallel labels are placed at that meridian. Alternatively, the pull-down menu can be used to specify a longitude location. If **east** is chosen, parallel labels are placed at the

maximum map longitude limit. If `west` is chosen, parallel labels are placed at the minimum map longitude limit.

The **Decimal Round** edit boxes are used to specify the power of ten to which the meridian and parallel labels are rounded. For example, a value of -1 results in labels displayed to the tenths decimal place.

The **Accept** button accepts any modifications that have been made to the meridian and parallel label properties and return to the Map Label Properties dialog box. Changes are applied to the current map only when the **Apply** button on the **Projection Control** dialog box is pushed.

The **Cancel** button disregards any modifications to the meridian and parallel labels and returns to the Map Label Properties dialog box.

The **Map Geoid** edit box is used to specify the geoid (ellipsoid) definition for the current map axes. The geoid is defined by a two-element vector of the form [semimajor-axis eccentricity]. Eccentricity must be a value between 0 and 1, but not equal to 1. A nonzero eccentricity represents an ellipsoid. The default geoid is a sphere with radius 1, represented as [1 0]. If a scalar entry is provided, it is assumed to be the radius of a sphere.

The **Accept** button accepts any modifications that have been made to the map geoid and return to the Projection Control dialog box. Changes are applied to the current map only when the **Apply** button on the Projection Control dialog box is pushed.

The **Cancel** button disregards any modifications to the map geoid and returns to the Projection Control dialog box.

See Also

axesm

Introduced in R2007a

clmo-ui

GUI to clear mapped objects

Activation

| Command Line | Maptool |
|-------------------|--------------------------------------|
| <code>clmo</code> | Tools > Delete > Object |

Description

`clmo` brings up a Select Object dialog box for selecting mapped objects to delete.

Controls

The scroll box is used to select the desired objects from the list of mapped objects.



Pushing the **Select all** button highlights all objects in the scroll box for selection. Pushing the **OK** button deletes the selected objects from the map. Pushing the **Cancel** button aborts the operation.

See Also

`clmo`

Introduced in R2007a

clrmenu

Add colormap menu to figure window

Activation

| Command Line |
|-------------------------|
| <code>clrmenu</code> |
| <code>clrmenu(h)</code> |

Description

`clrmenu` adds a colormap menu to the current figure.

`clrmenu(h)` adds a colormap menu to the figure specified by the handle `h`.

Controls

The following choices are included on the colormap menu:

Parula, **Gray**, **Hsv**, **Hot**, **Pink**, **Cool**, **Bone**, **Jet**, **Copper**, **Spring**, **Summer**, **Autumn**, **Winter**, **Flag**, and **Prism** generate colormaps.

Rand is a random colormap.

Brighten increases the brightness.

Darken decreases the brightness.

Flipud inverts the order of the colormap entries.

fliplr interchanges the red and blue components.

Permute permutes the colormap: red > blue, blue > green, green > red.


Define allows a workspace variable to be specified for the colormap.

Remember stores the current colormap.

Restore reverts to the stored colormap (initially, the stored colormap is the colormap in use when `cl rmenu` is invoked).

Refresh redraws the current figure window.

Digital Elevation activates the DEM Colormap Input dialog box. Use it to specify a colormap for a digital elevation map, and then apply the colormap to the current figure. The number of land and sea colors in the colormap is appropriate for the maximum elevations and depths of the data grid. The dialog box is shown and described below:



The **Mode** selection buttons are used to specify whether the length of the colormap is specified or whether the altitude range increment assigned to each color is specified.

The **Map variable** edit box is used to specify the data grid containing the elevation data.

The **Colormap Size** edit box is used in Size mode. This entry defines the length of the colormap. If omitted, a default length of 64 is used. This entry must be a scalar value.

The **Altitude Range** edit box is used in Range mode. This entry defines the altitude range increment assigned to each color. If omitted, a default increment of 100 is used. This entry must be a scalar value.

The **RGB Sea** edit box is used to define colors for data with negative values. The actual sea colors of the generated colormap are interpolated from this matrix. This entry can be

a matrix of any length (n -by-3) The colormap matrix of the current figure can be used by entering 'window' in this box. The `demcmap` function provides default sea colors, which are used if this entry is left blank.

The **RGB Land** edit box is used to define colors for data with positive values. The actual land colors of the generated colormap are interpolated from this matrix. This entry can be a matrix of any length (n -by-3). The colormap matrix of the current figure can be used by entering 'window' in this box. The `demcmap` function provides default sea colors, which are used if this entry is left blank.

Pressing the **Apply** button accepts the input data, creates the colormap, and assigns it to the current figure.

Pressing the **Cancel** button disregards any input data and closes the DEM Colormap Input dialog box.

See Also

`demcmap`

Introduced before R2006a

colorm

Create index map colormaps

Note colorm will be removed in a future release.


Syntax

```
colorm(datagrid, refvec)
```

Description

`colorm(datagrid, refvec)` displays the data grid in a new figure window and allows a colormap to be edited and saved to a new variable. `datagrid` and `refvec` are the data grid and the referencing vector of the surface. `map` must have positive index values into the colormap.

Controls



The `colorm` tool displays the surface map data in a new figure window with the current colormap. **Zoom** and **Colormaps** menus are activated for that figure.

The **Zoom On/Off** menu toggles interactive zoom on and off.

The **Colormaps** menu provided a variety of colormap options that can be applied to the map. See `clrmenu` in this guide for a description of the **Colormaps** menu options.

The **Load** button activates a dialog box, used to specify a colormap variable to be applied to the displayed surface map. This colormap can then be edited and saved.

The **Select** button activates the mouse cursor and allows a point on the map to be selected. The value of that point then appears in the **Codes** pull-down menu. The color of the selected point appears in the **Color** pull-down menu and can then be edited.

The **Codes** pull-down menu is used to select a particular value in the data grid. The color associated with that value then appears in the **Color** pull-down menu and can be edited.

The **Color** pull-down menu is used to select a particular color to assign to the value currently displayed in the Codes pull-down menu. A custom color can be defined by selecting the **custom** option. This brings up a custom color interface with which an RGB triple can be selected.

The **Save** button is used to save the modified colormap to the workspace. A dialog box appears in which the colormap variable name is entered.

See Also

`encodem` | `getseeds` | `maptrim` | `seedm`

Introduced before R2006a

demdataui

UI for selecting digital elevation data

Syntax

demdataui


Description

demdataui is a graphical user interface to extract digital elevation map data from a number of external data files. You can extract data to MAT-files or the base workspace as regular data grids with referencing vectors.

The demdataui panel lets you read data from a variety of high-resolution digital elevation maps (DEMs). These DEMs range in resolution from about 10 kilometers to 100 meters or less. The data files are available over the Internet at no cost, or (in some cases) on CD-ROMs for varying fees. demdataui reads ETOPO5, TerrainBase, GTOPO30, GLOBE, satellite bathymetry, and DTED data. See the links under See Also for more information on these data sets. demdataui looks for these geospatial data files on the MATLAB path and, for some operating systems, on CD-ROM disks.

You use the list to select the source of data and the map to select the region of interest. When you click the **Get** button, data is extracted and displayed on the map. Use the **Save** button to save the data in a MAT-file or to the base workspace for later display. The **Close** button closes the window.

Controls



The Map

The map controls the geographic extent of the data to be extracted. `demdataui` extracts data for areas currently visible on the map. Use the mouse to zoom in or out to the area of interest. See [zoom](#) for more on zooming.

Some data sources divide the world up into tiles. When extracting, data is concatenated across all visible tiles. The map shows the tiles in light yellow with light gray edges. When data resolution is high, extracting data for large area can take much time and memory. An approximate count of the number of points is shown above the map. Use the **Samplefactor** slider to reduce the amount of data.

The List

The list controls the source of data to be extracted. Click a name to see the geographic coverage in light yellow. The sources list shows the data sources found when `demdataui` started.

`demdataui` searches for data files on the MATLAB path. On some computers, `demdataui` also checks for data files on the root level of letter drives. `demdataui` looks for the following data: `etopo5`: `new_etopo5.bin` or `etopo5.northern.bat` and `etopo5.southern.bat` files. `tbase`: `tbase.bin` file. `satbath`: `topo_6.2.img` file. `gtopo30`: a folder that contains subfolders with the data files. For example, `demdataui` would detect `gtopo30` data if a folder on the path contained the folders `E060S10` and `E100S10`, each of which holds the uncompressed data files. `globedem`: a folder that contains data files and in the subfolder `/esri/hdr` and the `*.hdr` header files. `dted`: a folder that has a subfolder named `DTED`. The contents of the `DTED` folder are more subfolders organized by longitude and, below that, the `DTED` data files for each latitude tile. See the help for functions with the data source names for more on the data attributes and internet locations.

The Samplefactor Slider

The **Sample Factor** slider allows you to reduce the density of the data. A sample factor of 2 returns every second point. The current sample factor is shown on the slider.

The Get Button

The **Get** button reads the currently selected data and displays it on the map. Press the standard interrupt key combination for your platform to interrupt the process.

The Clear Button

The **Clear** button removes any previously read data from the map.

The Save Button

The **Save** button saves the currently displayed data to a MAT-file or the base workspace. If you choose to save to a file, you will be prompted for a file name and location. If you choose to save to the base workspace, you can choose the variable name under which the data will be stored.

Data are returned as Mapping Toolbox Version 1 display structures. For information about display structure format, see “Version 1 Display Structures” on page 1-257 in the reference page for `displaym`.

Use `load` and `displaym` to redisplay the data from a file on a map axes. To display the data in the base workspace, use `displaym`. To gain access to the data matrices, subscript into the structure (for example, `datagrid = demdata(1).map; refvec = demdata(1).maplegend`). Use `worldmap` to create easy displays of the elevation data (for example, `worldmap(datagrid, refvec)`). Use `meshm` to add regular data grids to existing displays, or `surfm` or a similar function for geolocated data grids (for example, `meshm(datagrid, refvec)` or `surfm(latgrat, longrat, z)`).

The Close Button

The **Close** button closes the `demdataui` panel.

See Also

`dted` | `etopo` | `globedem` | `gtopo30` | `satbath` | `tbase` | `vmap0ui`

Introduced before R2006a

handlem-ui

GUI for selecting mapped objects

Activation

| Command Line |
|------------------------------------|
| <code>h = handlem</code> |
| <code>h = handlem('prompt')</code> |

Description

`h = handlem` brings up a Select Object dialog box, which lists all currently displayed objects. Returns the selected objects.

`h = handlem('prompt')` brings up a Specify Object dialog box, which allows greater control of object selection.

Controls

Select Object Dialog Box



The scroll box is used to select the desired objects from the list of mapped objects. Pushing the **Select all** button highlights all objects in the scroll box for selection. Pushing the **OK** button returns the object in the variable `h`. Pushing the **Cancel** button aborts the operation.

Specify Object Dialog Box



The **Object** Controls are used to select an object type or tag. The **Name** pull-down menu is used to select from a list of predefined objects. The **Other Tag** edit box is used to specify an object tag not listed in the **Name** pull-down menu. Pushing the **Select** button brings up the Select Object dialog box, which shows only the currently displayed objects for selection.

The **Match** Controls are used when a graphics object type (image, line, surface, patch, or text) is specified. The **Untagged Objects** selection button is used to return only those objects with empty tag properties. The **All Objects** selection button is used to return all objects of the specified type, regardless of whether they are tagged.

Pushing the **Apply** button returns the specified objects. Pushing the **Cancel** button aborts the operation.

See Also

handlem

Introduced in R2007a

hidem-ui

Hide specified mapped objects

Activation

| Command Line | Maptool |
|--------------|-----------------------|
| hidem | Tools > Hide > Object |

Description

hidem brings up a Select Object dialog box for selecting mapped objects to hide (Visible property set to 'off').

Controls



The scroll box is used to select the desired objects from the list of mapped objects. Pushing the **Select all** button highlights all objects in the scroll box for selection. Pushing the **OK** button changes the *Visible* property of the selected objects to 'off'. Pushing the **Cancel** button aborts the operation without changing any properties of the selected objects.

See Also

hidem

Introduced in R2007a

lightmui

Control position of lights on globe or 3-D map

Note `lightmui` has been removed. Use `lightm` instead.

Syntax

```
lightmui(hax)
```

Description

`lightmui(hax)` creates a GUI to control the position of lights on a globe or 3-D map in map axes `hax`. You can control the position of lights by clicking and dragging the icon or by dialog boxes. Right-click the appropriate icon in the GUI to invoke the corresponding dialog box. You can change the light color by entering the RGB components manually or by clicking the pushbutton.

See Also

`lightm`

Introduced before R2006a

maptool

Add menu-activated tools to map figure

Activation

| Command Line |
|--|
| <code>maptool(<i>PropertyName</i>,<i>PropertyValue</i>)</code> |
| <code>maptool(<i>ProjectionFile</i>,...)</code> |
| <code>h = maptool(...)</code> |

Description


`maptool` adds several items to the menu in the current figure window with a map axes and opens the Projection Control dialog box for defining map projection and display properties. The figure window features a special menu bar that provides access to most of Mapping Toolbox capabilities.

`maptool(PropertyName,PropertyValue,...)` creates a figure window with a map axes defined by the supplied map properties. The `MapProjection` property must be the first input pair. `maptool` supports the same map properties as `axesm`.

`maptool(ProjectionFile,PropertyName, PropertyValue,...)` allows for the omission of the `MapProjection` property name. *ProjectionFile* must be the identifier of an available map projection.

`h = maptool(...)` returns a two-element vector containing the handle of the `maptool` figure window and the handle of the map axes.

Controls



Map Menu

The **Lines** option activates the Line Map Input dialog box for projecting two- and three-dimensional line objects onto the map axes.

The **Patches** option activates the Patch Map Input dialog box for projecting patch objects onto the map axes.

The **Regular Surfaces** option activates the Mesh Map Input dialog box for projecting a regular data grid onto a graticule projected onto the map axes.

The **General Surfaces** option activates the Surface Map Input dialog box for projecting a geolocated data grid onto the map axes.

The **Contours** option activates the Contour Map Input dialog box for projecting a two- or three-dimensional contour plot onto the map axes.

The **Quiver 2D** option activates the Quiver Map Input dialog box for projecting a two-dimensional quiver plot onto the map axes.

The **Quiver 3D** option activates the Quiver3 Map Input dialog box for projecting a three-dimensional quiver plot onto the map axes.

The **Stem** option activates the Stem Map Input dialog box for projecting a stem plot onto the map axes.

The **Scatter** option activates the Scatter Map Input dialog box for projecting a scatter plot onto the map axes.

The **Text** option activates the Text Map Input dialog box for projecting text objects onto the map axes.

Display Menu

The **Projection** option activates the Projection Control dialog box for editing map projection properties and map display settings.

The **Graticule** option is used to view and edit the graticule size for surface maps.

The **Legend** option is used to display a contour map legend.

The **Frame** option is used to toggle the map frame on and off.

The **Grid** option is used to toggle the map grid on and off.

The **Meridian Labels** option is used to toggle the meridian grid labels on and off.

The **Parallel Labels** option is used to toggle the parallel grid labels on and off.

The **Tracks** option activates the Define Tracks input box for calculating and displaying Great Circle and Rhumb Line tracks on the map axes.

The **Small Circles** option activates the Define Small Circles input box for calculating and displaying small circles on the map axes.

The **Surface Distances** option activates the Surface Distance dialog box for distance, azimuth, and reckoning calculations.

Tools Menu

The **Hide** option is used to hide the mouse tool buttons.

The **Off** option is used to turn off the current mouse tool.

The **Set Limits** option is used to define the zoom out limits to the current settings on the axes.

The **Full View** option is used to zoom out to the current axes limit settings.

The **Origin** option is used to toggle Origin (`originui`) mode on and off. Origin mode is used to interactively modify the map origin.

The **2D View** option is used to set the default two-dimensional view (`azimuth=0`, `elevation=90`).

The **Objects** option activates the Object Sets dialog box, which allows for property manipulation of objects displayed on the map axes.

The **Edit** option activates the MATLAB Property Editor to manipulate properties of a plotted object. Choose the **Current Object** option to edit the currently selected object or choose the **Select Object** option to open the Select Object dialog box and choose the object you want to edit.

The **Show** option is used to set the `Visible` property of mapped objects to 'on'. The **All** option shows all currently mapped objects. The **Object** option activates the Select Object dialog box.

The **Hide** option is used to set the `Visible` property of mapped objects to 'off'. Choose from the **All** or **Map** options, or choose the **Object** option to activate the Select Object dialog box.

The **Delete** option is used to clear the selected objects. The **All** option clears the current map, frame, and grid lines. The map definition is left in the axes definition. The **Map** option clears the current map, deleting objects plotted on the map but leaving the frame and grid lines displayed. The **Object** option activates the Select Object dialog box.

The **Axes** option is used to manipulate the MATLAB Cartesian axes. The **Show** option shows this axes, the **Hide** option hides this axes, and the **Color** option allows for custom color selection for this axes.

Colormaps Menu

The **Colormaps** menu allows for manipulation of the colormap for the current figure. See the `clmenu` reference page for details on the **Colormaps** menu options.

See Also

`axesm`

Introduced before R2006a

maptrim

Interactively trim and convert map data from vector to raster format

Syntax

```
maptrim(lat,lon,linestyle)
maptrim(datagrid,refvec)
maptrim(datagrid,refvec,PropertyName,PropertyValue)
```

Description


`maptrim(lat,lon)` displays the supplied map data in a new figure window and allows a region of the map to be selected and saved in the workspace. `lat` and `lon` must be vector map data. The output can be line, patch, or regular surface (matrix) data. If patch map output is selected, the inputs `lat` and `lon` must originally be patch map data.

`maptrim(lat,lon,linestyle)` displays the supplied map, where `linestyle` defines the type of line used, specified as a `linespec`.

`maptrim(datagrid,refvec)` displays data grid data in a new figure window and allows a subset of this map to be selected and saved. The output is regular surface data.

`maptrim(datagrid,refvec,PropertyName,PropertyValue)` displays the data grid using the surface properties provided. The object `Tag`, `EdgeColor`, and `UserData` properties cannot be set.


Controls



The `maptrim` tool displays the supplied map data in a new figure window and activates a **Customize** menu for that figure. The **Customize** menu has three menu options: **Zoom On/Off**, **Limits**, and **Save As**.

The **Zoom On/Off** menu toggles interactive zoom on and off.

The **Limits** menu option activates the Enter Map Limits dialog box, which is used to enter the latitude and longitude limits of the desired map subset. These entries are two-element vectors, enclosed in brackets. Pressing the **OK** button zooms in to the new limits. Pressing the **Cancel** button disregards the new limits and returns to the map display.



The **Save As** menu option is used to specify the variable names in which to save the map data subset. To save line and patch data, enter the new latitude and longitude variable names, along with the map resolution. For surface data, enter the new map and referencing vector variable names, along with the scale of the map. Latitude and longitude limits are optional.

See Also

`maptriml` | `maptrimp` | `maptrims`

Introduced before R2006a

mlayers

GUI to control plotting of display structure elements

Note `mlayers` will be removed in a future release.

Activation

| Command Line | Maptool |
|------------------------------------|----------------------------|
| <code>mlayers('filename')</code> | Session > Layers |
| <code>mlayers('filename',h)</code> | |
| <code>mlayers(cellarray)</code> | |
| <code>mlayers(cellarray,h)</code> | |

Description


`mlayers('filename')` associates all display structures, which in this context are also called map layers, in the MAT-file `filename` with the current map axes. The display structure variables are accessible only through the `mlayers` tool, and not through the base workspace. `filename` must be a character vector.

`mlayers('filename',h)` assigns the layers found in `filename` to the map axes indicated by the handle `h`.

`mlayers(cellarray)` associates the layers specified by `cellarray` with the current map axes. `cellarray` must be of size `n` by 2. Each row of `cellarray` represents a map layer. The first column of `cellarray` contains the layer structure, and the second column contains the name of the layer structure. Such a cell array can be generated from data in the current workspace with the function `rootlayr`. In this case, the calling sequence would be `rootlayr; mlayers(ans)`.

`mlayers(cellarray,h)` assigns the layers specified by `cellarray` to the map axes specified by the handle `h`.

Controls



The scrollable list box displays all of the map layers currently associated with the map axes. An asterisk next to the layer name indicates that the layer is currently visible. An h next to the layer name indicates a layer that is plotted, but currently hidden.

The **Plot** button plots the selected map layer. Once the selected layer is plotted, the button toggles between **Hide** and **Show**, to turn the `Visible` property of the plotted objects to 'off' and 'on', respectively.

The **Zdata** button activates the Specify Zdata dialog box, which is used to enter the workspace variable containing the `ZData` for the selected map layer. Pressing the **List** button produces a list of all current workspace variables, from which the `ZData` variable can be selected. This entry can also be a scalar.




The **Highlight** button is used to toggle the selected map layer between highlighted and normal display.

The **Members** button brings up a list of members of the selected map layer. Members of a layer are defined by their `Tag` property.

The **Delete** button deletes the selected map layer from the map.

The **Property** button activates the Define Layer Properties dialog box, which is used to specify or change properties of all objects in the selected map layer. Character vector entries must be enclosed in single quotes.



The **Purge** button deletes the selected map layer from the mlayers tool. Selecting **Yes** from the Confirm Purge dialog box deletes the map layer from both the mlayers tool and the map display. Selecting **Data Only** from the Confirm Purge dialog box deletes the map layer from the mlayers tool, while retaining the plotted object on the map display.

See Also

mobjects | rootlayr

Introduced before R2006a

objects

Manipulate object sets displayed on map axes

Note `objects` will be removed in a future release.

Activation

| Command Line | Maptool |
|-------------------------|---------------------------|
| <code>objects</code> | Tools > Objects |
| <code>objects(h)</code> | |

Description

An object set is defined as all objects with identical tags. If no tags are supplied, object sets are defined by object type.

`objects` allows manipulation of the object sets on the current map axes.

`objects(h)` allows manipulation of the objects set on the map axes specified by the handle `h`.

Controls



The scrollable list box displays all of the object sets associated with the map axes. An asterisk next to an object set name indicates that the object set is currently visible. An h next to an object set name indicates an object set that is plotted, but currently hidden. The order shown in the list indicates the stacking order of objects within the same plane.

The **Hide/Show** button toggles the `Visible` property of the selected object set to 'off' and 'on', respectively, depending on the current `Visible` status.

The **Zdata** button activates the Specify Zdata dialog box, which is used to enter the workspace variable containing the `ZData`. The `ZData` property is used to specify the plane in which the selected object set is drawn. Pressing the **List** button produces a list of all current workspace variables, from which the `ZData` variable can be selected. Alternatively, a scalar value can be entered instead of a variable.




The **Highlight** button highlights all objects belonging to the selected object set.

The **Tag** button brings up an Edit Tag dialog box, which allows the tag of all members of the selected object set to be modified.

The **Delete** button clears all objects belonging to the selected object set from the map. The cleared object set remains associated with the map axes.



The **Property** button activates the Define Object Properties dialog box, which is used to specify additional properties of all objects in the selected object set. Character vector entries must be enclosed in single quotes.



The **Update** button updates the list box display with current objects sets.

The **Stacking Order** buttons are used to modify the drawing order of the selected object set in relation to other plotted object sets in the same plane. Objects drawn first appear at the bottom of the stack, and objects drawn last appear at the top of the stack. The **Top** button places the selected object set above all other object sets in its plane. The **Up** and **Dwn** buttons move the selected object set up and down one place in the stacking order, respectively. The **Btm** button places the selected object set below all other object sets in its plane. Note that the **ZData** property overrides stacking order, i.e., if an object is at the top of the stacking order for its plane, it can still be covered by an object drawn in a higher plane.

See Also

`mlayers`

Introduced before R2006a

originui

Interactively modify map origin

Activation

| Command Line | Maptool |
|--------------|---|
| originui | Tools > Origin (menu) > Origin(button) |
| originui on | |
| originui off | |

Description

originui provides a tool to modify the origin of a displayed map projection. A marker (dot) is displayed where the origin is currently located. This dot can be moved and the map reprojected with the identified point as the new origin.

originui automatically toggles the current axes into a mode where only actions recognized by originui are executed. Upon exit of this mode, all prior ButtonDown functions are restored to the current axes and its children.

originui on activates origin tool. originui off e-activates the tool. originui will toggle between these two states.

Controls

Keystrokes

originui recognizes the following keystrokes. **Enter** (or **Return**) will reproject the map with the identified origin and remain in the originui mode. **Delete** and **Escape** will exit the origin mode (same as originui off). **N,S,E,W** keys move the marker North, South, East or West by 10.0 degrees for each keystroke. **n,s,e,w** keys move the marker in the respective directions by 1 degree per keystroke.

Mouse Actions

`originui` recognizes the following mouse actions when the cursor is on the origin marker.

- Single-click and hold moves the origin marker. Double-click the marker reprojects the map with the specified map origin and remains in the origin mode (same as `originui Return`).
- Extended-click moves the marker along the Cartesian X or Y direction only (depending on the direction of greatest movement).
- Alternate-click exits the origin tool (same as `originui off`).

Macintosh Key Mapping

- Extend-click: **Shift**+click mouse button
- Alternate-click: **Option**+click mouse button

Microsoft Windows Key Mapping

- Extend-click: **Shift**+click left button or both buttons
- Alternate-click: **Ctrl**+click left button or right button

X-Windows Key Mapping

- Extend-click: **Shift**+click left button or middle button
- Alternate-click: **Ctrl**+click left button or right button

See Also

`axesm` | `setm`

Introduced before R2006a

panzoom

Zoom settings on 2-D map

Note panzoom will be removed in a future release. Use zoom instead.

Syntax

```
panzoom
panzoom on
panzoom off
panzoom setlimits
panzoom out
panzoom fullview
```

Description

panzoom toggles the pan and zoom tool on and off.

panzoom on is equivalent to zoom on.

panzoom off is equivalent to zoom off.

panzoom setlimits is equivalent to zoom reset.

panzoom out is equivalent to zoom out.

panzoom fullview sets the axes limit modes to 'auto' and resets zoom to the resulting limits.

See Also

zoom

Introduced before R2006a

parallelui

Interactively modify map parallels

Activation

| Command Line | Maptool |
|----------------|------------------------------------|
| parallelui | Tools > Parallels (menu) |
| parallelui on | |
| parallelui off | |

Description

parallelui toggles the parallel tool on and off.

parallelui on activates the parallel tool

parallelui off deactivates the parallel tool

The parallelui GUI provides a tool to modify the standard parallels of a displayed map projection. One or two red lines are displayed where the standard parallels are currently located. The parallel lines can be dragged to new locations, and the map reprojected with the locations of the parallel lines as the new standard parallels.

Controls

Mouse Interaction

A single-click-and-drag moves the parallel lines. A double-click on one of the standard parallels reprojects the map using the new parallel locations.

See Also

axesm | setm

Introduced before R2006a

property editors

GUIs to edit properties of mapped objects

Activation

| | |
|--------------|---|
| map display: | Alternate-click mapped object (for Click-and-Drag Property Editor) |
| | In plot edit mode, double-click mapped object (to obtain MATLAB Property Editor; click the More Properties... button to open the Property Inspector) |
| maptool: | Tools > Edit Plot menu item (for MATLAB Property Editor) |

Description


Alternate (e.g., **Ctrl**+clicking a mapped object activates a property editor, which allows modification of some basic properties of the object through simple mouse clicks and drags. The objects supported by this editor are map axes, lines, text, patches, and surfaces, and the properties supported for each object type are shown below.

In plot edit mode, double-clicking a mapped object activates the MATLAB Property Editor for that object. From the Property Editor you can launch the Property Inspector, a GUI that lists the properties and values of the selected object and allows you to modify them.

Controls

Click-and-Drag Property Editor

The Click-and-Drag editor lists object properties and values. The object tag appears at the top of the editor. Property names and values that appear in blue are toggles. For example, clicking **Frame** in the axes editor toggles the value of the Frame property between 'on' and 'off'.



Click-and-Drag Editor for a map axes

Property values that appear on the right side of the editor box are modified by clicking and dragging. For example, to change the **MarkerColor** property of a line object, click and hold the dot next to **MarkerColor**, and drag the cursor until the dot appears in the desired color.



Click-and-Drag Editor for a line object

The **Drag** control in the text editor is used to reposition the text character vector. In drag mode, use the mouse to move the text to a new location, and click to reposition the text. The **Edit** control in the text editor activates a **Text Edit** window, which is used to modify text.



Click-and-Drag Editor for a text object

The **Marker** property name in the patch editor is used to toggle the marker on and off. The property value to the right of **Marker** can be modified by clicking and dragging until the desired marker symbol appears.




Click-and-Drag Editor for a patch object

The **Graticule** control on the surface editor activates a Graticule Mesh dialog box, which is used to alter the size of the graticule.


To move the property editor around the figure window, hold down the **Shift** key while dragging the editor box. Alternate-clicking the background of the property editor closes the **Click-and-Drag** editing session.

Guide Property Editor

The MATLAB Property Inspector (the `inspect` function) allows you to view and modify property values for most properties of the selected object. Use it to expand and collapse the hierarchy of objects, showing an object's parents and children. A plus sign (+) before a property indicates that it can be expanded to show its components, for example the axes `AmbientLightColor` applied to the surface object displayed below. A minus sign (-) before an object indicates an object can be collapsed to hide its components. To activate the Object Browser, check the **Show Object Browser** check box. The **Property List** shows all the property names of the selected object and their current values. To activate the **Property List**, check the **Show Property List** check box. To change a property value, use the edit boxes above the Property List. Pressing the **Close** button closes the Guide Property Editor and applies the property modifications to the object.



A lit surface object in a map axes



Property Inspector view of axes object

See Also

[inspect](#) | [propedit](#) | [uimaptbx](#)

Introduced before R2006a

qrydata

GUI to interactively perform data queries

Note `qrydata` will be removed in a future release.

Activation

| Command Line |
|---|
| <code>qrydata(cellarray)</code> |
| <code>qrydata(titlestr,cellarray)</code> |
| <code>qrydata(h,cellarray)</code> |
| <code>qrydata(h,titlestr,cellarray)</code> |
| <code>qrydata(...,cellarray1,cellarray2,...)</code> |

Description

A data query is used to obtain the data corresponding to a particular (x,y) or (lat,lon) point on a standard or map axes.

`qrydata(cellarray)` activates a data query dialog box for interactive queries of the data set specified by `cellarray` (described below). `qrydata` can be used on a standard axes or a map axes. (x,y) or (lat,lon) coordinates are entered in the dialog box, and the data corresponding to these coordinates is then displayed.

`qrydata(titlestr,cellarray)` uses `titlestr` as the title of the query dialog box.

`qrydata(h,cellarray)` and `qrydata(h,titlestr,cellarray)` associate the data queries with the axes specified by the handle `h`, which in turn allows the input coordinates to be specified by clicking the axes.

The input `cellarray` is used to define the data set and the query. The first cell must contain a character vector that is the label of the data display line. The second cell must

contain a character vector that specifies the type of query operation. The operation can be either a predefined operation or a valid user-defined function name. The predefined query operations are 'matrix', 'vector', 'mapmatrix', and 'mapvector'.

The 'matrix' query uses the MATLAB `interp2` function to find the value of the matrix *Z* at the input (*x*, *y*) point. The format of the `cellarray` input for this query is: {'label', 'matrix', *X*, *Y*, *Z*, *method*}. *X* and *Y* are matrices specifying the points at which the data *Z* is given. The rows and columns of *X* and *Y* must be monotonic. *method* is an optional argument that specifies the interpolation method. Possible *method* values are 'nearest', 'linear', or 'cubic'. The default is 'nearest'.

The 'vector' query uses the `interp2` function to find the value of the matrix *Z* at the input (*x*, *y*) point, then uses that value as an index to a data vector. The value of the data vector at that index is returned by the query. The format of `cellarray` for this type of query is: {'label', 'vector', *X*, *Y*, *Z*, vector}. *X* and *Y* are matrices specifying the points at which the data *Z* is given. The rows and columns of *X* and *Y* must be monotonic. `vector` is the data vector.


The 'mapmatrix' query interpolates to find the value of the map at the input (*lat*, *lon*) point. The format of `cellarray` for this query is: {'label', 'mapmatrix', *datagrid*, *refvec*, *method*}. *datagrid* and *refvec* are the data grid and the corresponding referencing vector. *method* is an optional argument that specifies the interpolation method. Possible *method* values are 'nearest', 'linear', or 'cubic'. The default is 'nearest'.

The 'mapvector' query interpolates to find the value of the map at the input (*lat*, *lon*) point, then uses that value as an index to a data vector. The value of the vector at that index is returned by the query. The format of `cellarray` for this type of query is {'label', 'mapvector', *datagrid*, *refvec*, vector}. *datagrid* and *refvec* are the data grid and the corresponding referencing vector. `vector` is the data vector.

User-defined query operations allow for functional operations using the input (*x*, *y*) or (*lat*, *lon*) coordinates. The format of `cellarray` for this type of query is {'label', *function*, other arguments...} where the other arguments are the remaining elements of `cellarray` as in the four predefined operations above. *function* is a user-created function and must refer to a MATLAB function with the signature `z = fcn(x,y,other_arguments...)`.

`qrydata(..., cellarray1, cellarray2, ...)` is used to input multiple cell arrays. This allows more than one data query to be performed on a given point.

Controls



Sample data query dialog box

If an axes handle `h` is not provided, or if the axes specified by `h` is not a map axes, the currently selected point is labeled as **Xloc** and **Yloc** at the top of the query dialog box. If `h` is a map axes, the current point is labeled as **Lat** and **Lon**. Displayed below the current point are the results from the queries, each labeled as specified by the `'label'` input arguments.

The **Get** button appears if an axes handle `h` is provided. Pressing this button activates a mouse cursor, which is used to select the desired point by clicking the axes. Once a point is selected, the queries are performed and the results are displayed.

The **Process** button appears if the handle `h` is not provided. In this case, the (x, y) coordinates of the desired point are entered into the edit boxes. Pressing the **Process** button performs the data queries and displays the results.

Pressing the **Close** button closes the query dialog box.

Examples


This example illustrates use of a user-defined query to display city names for map points specified by a mouse click. The query is evaluated by a user-supplied file called `qrytest.m`, described below:

```
axesm miller
land = shaperead('landareas', 'UseGeoCoords', true);
geoshow(land, 'FaceColor', [0.5 0.7 0.5])
lakes = shaperead('worldlakes', 'UseGeoCoords', true);
geoshow(lakes, 'FaceColor', 'blue')
rivers = shaperead('worldrivers', 'UseGeoCoords', true);
geoshow(rivers, 'Color', 'blue')
cities = shaperead('worldcities', 'UseGeoCoords', true);
geoshow(cities, 'Marker', '.', 'Color', 'red')
tightmap
```

```
lat = [cities.Lat]';  
lon = [cities.Lon]';  
mat = char(cities.Name);  
qrydata(gca,'City Data',{ 'City', 'qrytest', lat, lon, mat})
```

Create the file `qrytest.m` on your path, and in it put the following code:

```
function cityname = qrytest(lt, lg, lat, lon, mat)  
% function QRYTEST returns city name for mouse click  
% QRYTEST will find the closest city (min radius) from  
% the mouse click, within an angle of 5 degrees.  
%  
latdiff = lt-lat;  
londiff = lg-lon;  
rad = sqrt(latdiff.^2+londiff.^2);  
[minrad,index] = min(rad);  
if minrad > 5  
    index = [];  
end  
switch length(index)  
    case 0, cityname = 'No city located near click';  
    case 1, cityname = mat(index,:);  
end
```



Clicking the mouse over a city marker displays the name of the selected city. Clicking the mouse in an area away from any city markers displays 'No city located near click'.

See Also

`interp2`

Introduced before R2006a

scirclui

GUI to display small circles on map axes

Note scirclui is obsolete. Use scircleg instead.

Activation


| Command Line | Maptool |
|--------------|-----------------------------|
| scirclui | Display mall Circles |
| scirclui(h) | |

Description

scirclui activates the Define Small Circles dialog box for adding small circles to the current map axes.

scirclui(h) activates the Define Small Circles dialog box for adding small circles to the map axes specified by the axes handle h.

Controls



Define Small Circles dialog box for one-point mode

The **Style** selection buttons are used to specify whether the circle radius is a constant great circle distance or a constant rhumb line distance.

The **Mode** selection buttons are used to specify whether one point or two points are to be used in defining the small circle. If one-point mode is selected, a center point, radius, and azimuth are the required inputs. If two-point mode is selected, a center point, and perimeter point on the circle are the required inputs.

The **Center Point** controls are used in both one-point and two-point mode. The **Lat** and **Lon** edit boxes are used to enter the latitude and longitude of the center point of the small circle to be displayed. These values must be in degrees. To display more than one small circle, a vector of values can be entered, enclosed in brackets in each edit box. Pushing the **Lat** or **Lon** button brings up an expanded edit box for easier entry of long vectors. The **Mouse Select** button is used to select a center point by clicking the displayed map. The coordinates of the selected point then appear in the **Lat** and **Lon** edit boxes and can be modified. The coordinates appear in degrees, regardless of the angle units defined for the current map projection.

The **Circle Point** controls are used only in two-point mode. The **Lat** and **Lon** edit boxes are used to enter the latitude and longitude of a point on the perimeter of the small circle to be displayed. These values must be in degrees. To display more than one small circle, a vector of values can be entered, enclosed in brackets in each edit box. Pushing the **Lat** or **Lon** button brings up an expanded edit box for easier entry of long vectors. The **Mouse Select** button is used to select a perimeter point by clicking the displayed map. The coordinates of the selected point then appear in the **Lat** and **Lon** edit boxes and can be modified. The coordinates appear in degrees, regardless of the angle units defined for the current map projection.

The **Size and Sector** controls are used only in one-point mode. The **Radius Units** button brings up a Define Range Units dialog box, which allows for modification of the small circle radius units and the normalizing geoid. The **Rad** edit box is used to enter the radius of the small circle in the proper units. The **Arc** edit box is used to specify the sector azimuth, measured in degrees, clockwise from due north. If the entry is omitted, a complete small circle is drawn. When entering radius and arc data for more than one small circle, vectors of values, enclosed in brackets, are entered in each edit box. Pushing the **Rad** or **Arc** button brings up an expanded edit box for that entry, which is useful for entering long vectors.

The **Z Plane** edit box is used to enter a scalar value that specifies the plane in which to display the small circles.

The **Other Properties** edit box is used to specify additional properties of the small circles to be projected, such as 'Color', 'b'. Character vector entries must be enclosed in quotes.

Pressing the **Apply** button accepts the input data and displays the small circles on the current map axes.

Pressing the **Cancel** button disregards any input data and closes the Define Small Circles dialog box.



This dialog box, available only in one-point mode, allows for modification of the small circle radius units and the normalizing geoid.

The **Radius Units** pull-down menu is used to select the units of the small circle radius. The unit selected is displayed near the top of the Define Small Circles dialog box, and all latitude and longitude entries must be entered in these units. Users must also be sure to specify the normalizing geoid in the same units. If radians are selected, it is assumed the radius entry is a multiple of the radius used to display the current map, as defined by the map geoid property.

The **Normalizing Geoid** edit box is used to modify the radius used to normalize the small circle radius to a radian value, which is necessary for proper calculations and map display. This entry must be in the same units as the small circle radius. If the small circle radius units are in radians, then the normalizing geoid must be the same as the geoid used for the current map axes.

Pressing the **Cancel** button disregards any modifications and closes the Define Radius Units dialog box.

Pressing the **Apply** button accepts any modifications and returns to the Define Small Circles dialog box.

See Also

`scircle1` | `scircle2`

Introduced before R2006a

seedm

GUI to fill data grids with seeded values

Note seedm will be removed in a future release.

Activation

Command Line


```
seedm(datagrid, refvec)
```

Description

Encoding is the process of filling in specific values in regions of a data grid up to specified boundaries, which are indicated by entries of 1 in the variable `map`. Encoding entire regions at one time allows indexed maps to be created quickly.

`seedm(datagrid, refvec)` displays the surface map in a new figure window and allows for seeds to be specified and the encoded map generated. The encoded map can then be saved to the workspace. `map` is the data grid and must consist of positive integer index values. `refvec` is the referencing vector of the surface.

Controls



The **Zoom On/Off** menu toggles the zoom box on and off. The box can be moved by clicking the new location or by dragging the box to the new location. The box size can be

increased or decreased by dragging a corner of the box. Pressing the **Return** key or double-clicking in the center of the box zooms in to the box limits.

The **Colormaps** menu provides a variety of colormap options that can be applied to the map. See `clrmenu` in this guide for a description of the **Colormaps** menu options.

The **Get** button allows mouse selection of points on the map to which seeds are assigned. The number of points to be selected is entered in the **# of Seeds** edit box. The value of the seed is entered in the **Value** edit box. This seed value is assigned to each point selected with the mouse. The **Get** button is pressed to begin mouse selection. After all the points have been selected, the **Fill In** button is pressed to perform the encoding operation. The region containing the seed point is filled in with the seed value. The **Reset** button is used to disregard all points selected with the mouse before the **Fill In** button is pressed.

Alternatively, specific map values can be globally replaced by using the **From/To** edit boxes. The value to be replaced is entered in the first edit box, and the new value is entered in the second edit box. Pressing the **Change** button replaces all instances of the **From** value to the **To** value in the map.

Note Values of 1 represent boundaries and should not be changed.

The **Save** button is used to save the encoded map to the workspace. A dialog box appears in which the map variable name is entered.

See Also

`colorm` | `encodem` | `getseeds` | `maptrim`

Introduced before R2006a

showm-ui

Show specified mapped objects

Activation

| Command Line | Maptool |
|--------------|-----------------------|
| showm | Tools > Show > Object |

Description

showm brings up a Select Object dialog box for selecting mapped objects to show (Visible property set to 'on').

Controls



The scroll box is used to select the desired objects from the list of mapped objects. Pushing the **Select all** button highlights all objects in the scroll box for selection. Pushing the **OK** button changes the Visible property of the selected objects to 'on'. Pushing the **Cancel** button aborts the operation without changing any properties of the selected objects.

See Also

showm

Introduced in R2007a

surfdist

Interactive distance, azimuth, and reckoning calculations

Activation

| Command Line | Maptool |
|--------------|--|
| surfdist | Display > Surface > Distances |
| surfdist(h) | |
| surfdist([]) | |


Description

surfdist activates the Surface Distance dialog box for the current axes only if the axes has a proper map definition. Otherwise, the Surface Distance dialog box is activated, but is not associated with any axes.

surfdist(h) activates the Surface Distance dialog box for the axes specified by the handle h. The axes must be a map axes.

surfdist([]) activates the Surface Distance dialog box and does not associate it with any axes, regardless of whether the current axes has a valid map definition.

Controls



The **Style** selection buttons are used to specify whether a great circle or rhumb line is used to calculate the surface distance. When all other entries are provided, selecting a style updates the surface distance calculation.

The **Mode** selection buttons are used to specify whether one point or two points are to be used in defining the track distance. If one-point mode is selected, a starting point, azimuth, and range are the required inputs, and the ending point is computed. If two-point mode is selected, starting and ending points of the track are required, and the azimuth and distance along this track are then computed.

The **Show Track** check box is used to indicate whether the track is shown on the associated map display. The track is deleted when the Surface Distance dialog box is closed, or when the **Show Track** check box is unchecked and the surface distance calculations are recomputed.

The **Starting Point** controls are used for both one-point and two-point mode. The **Lat** and **Lon** edit boxes are used to enter the latitude and longitude of the starting point of

the track. These values must be in degrees. Only one starting point can be entered. The **Mouse Select** button is used to select a starting point by clicking the displayed map. The coordinates of the selected point then appear in the **Lat** and **Lon** edit boxes and can be modified. The coordinates appear in degrees, regardless of the angle units defined for the current map projection.

The **Ending Point** controls are enabled only for two-point mode. The **Lat** and **Lon** edit boxes are used to enter the latitude and longitude of the ending point of the track. These values must be in degrees. Only one ending point can be entered. The **Mouse Select** button is used to select an ending point by clicking the displayed map. The coordinates of the selected point then appear in the **Lat** and **Lon** edit boxes and can be modified. The coordinates appear in degrees, regardless of the angle units defined for the current map projection. During one-point mode, the Ending Point controls are disabled, but the ending point that results from the surface distance calculation is displayed.


The **Direction** controls are enabled only for one-point mode. The **Range Units** button brings up a Define Range Units dialog box which allows for modification of the range units and the normalizing geoid. The **Az** edit box is used to enter the azimuth, which sets the initial direction of the track from the starting point. Azimuth is measured in degrees clockwise from due north. The **Rng** edit box is used to specify the reckoning range of the track, in the proper units. The azimuth and reckoning range, along with the starting point, are used to compute the ending point of the track in one-point mode. During two-point mode, the **Direction** controls are disabled, but the azimuth and range values resulting from the surface distance calculation are displayed.

Pressing the **Close** button disregards any input data, deletes any surface distance tracks that have been plotted, and closes the Surface Distance dialog box.

Pressing the **Compute** button accepts the input data and computes the specified distances.

Define Range Units Dialog Box

This dialog box, available only for one-point mode, allows for modification of the range units and the normalizing geoid.



The **Range Units** pull-down menu is used to select the units of the reckoning range. The unit selected is displayed near the top of the Surface Distance dialog box, and all latitude and longitude entries must be entered in these units. Users must also be sure to specify the normalizing geoid in the same units. If radians are selected, it is assumed the range entry is a multiple of the radius of the normalizing geoid. In this case, the normalizing geoid must be the same as the geoid used to display the current map.

The **Normalizing Geoid** edit box is used to modify the radius used to normalize range entries to radian values, which is necessary for proper calculations and map display. This entry must be in the same units as the range units. If the range units are in radians, then the normalizing geoid must be the same as the geoid used for the current map axes.

Pressing the **Cancel** button disregards any modifications and closes the Define Range Units dialog box.

Pressing the **Apply** button accepts any modifications and returns to the Surface Distance dialog box.

Introduced before R2006a

tagm-ui

GUI to edit tag property of mapped object

Activation

| Command Line |
|--------------|
| tagm |
| tagm(h) |

Description

tagm brings up a Select Object dialog box for selecting mapped objects and changing their Tag property. Upon selecting the objects, the Edit Tag dialog box is activated, in which the new tag is entered.

tagm(h) activates the Edit Tag dialog box for the objects specified by the handle h.

Controls



Select Object Dialog Box

The scroll box is used to select the desired objects from the list of mapped objects. Pushing the **Select all** button highlights all objects in the scroll box for selection. Pushing the **Ok** button activates the Edit Tag dialog box. Pushing the **Cancel** button aborts the operation without changing any properties of the selected objects.



Edit Tag Dialog Box

Enter the new tag character vector in the edit box. Pressing the **Apply** button changes the Tag property of all selected objects to the new tag character vector. Pressing the **Cancel** button closes the Edit Tag dialog box without changing the Tag property of the selected objects.

See Also

tagm

Introduced in R2007a

trackui

GUI to display great circles and rhumb lines on map axes

Note trackui is obsolete. Use trackg instead.

Activation


| Command Line | Maptool |
|--------------|----------------------------|
| trackui | Display > Tracks |
| trackui(h) | |

Description

trackui activates the Define Tracks dialog box for adding great circle or rhumb line tracks to the current map axes.

trackui(h) activates the Define Tracks dialog box for adding great circle or rhumb line tracks to the map axes specified by the axes handle h.

Controls



Define Tracks dialog box for two-point mode

The **Style** selection buttons are used to specify whether a great circle or rhumb line track is displayed.

The **Mode** selection buttons are used to specify whether one point or two points are to be used in defining the track. If one-point mode is selected, a starting point, azimuth, and range are the required inputs. If two-point mode is selected, starting and ending points are required.

The **Starting Point** controls are used for both one-point and two-point mode. The **Lat** and **Lon** edit boxes are used to enter the latitude and longitude of the starting point of the track to be displayed. These values must be in degrees. To display more than one track, a vector of values can be entered, enclosed in brackets in each edit box. Pushing the **Lat** or **Lon** button brings up an expanded edit box for easier entry of long vectors. The **Mouse Select** button is used to select a starting point by clicking the displayed map. The coordinates of the selected point then appear in the **Lat** and **Lon** edit boxes and can be modified. The coordinates appear in degrees, regardless of the angle units defined for the current map projection.

The **Ending Point** controls are used only for two-point mode. The **Lat** and **Lon** edit boxes are used to enter the latitude and longitude of the ending point of the track to be displayed. These values must be in degrees. To display more than one track, a vector of values can be entered, enclosed in brackets, in each edit box. Pushing the **Lat** or **Lon** button brings up an expanded edit box for easier entry of long vectors. The **Mouse Select** button is used to select an ending point by clicking the displayed map. The coordinates of the selected point then appear in the **Lat** and **Lon** edit boxes and can be modified. The coordinates appear in degrees, regardless of the angle units defined for the current map projection.


The **Direction** controls are used only for one-point mode. The **Range Units** button brings up a Define Range Units dialog box, which allows for modification of the range units and the normalizing geoid. The **Az** edit box is used to enter the azimuth, which sets the initial direction of the track from the starting point. Azimuth is measured in degrees clockwise from due north. The **Rng** edit box is used to specify the range of the track, in the proper units. If the range entry is omitted, a complete track is drawn. When inputting azimuth and range data for more than one track, vectors of values, enclosed in brackets, are entered in each edit box. Pushing the **Az** or **Rng** button brings up an expanded edit box for that entry, which is useful for entering long vectors.

The **Z Plane** edit box is used to enter a scalar value that specifies the plane in which to display the tracks.

The **Other Properties** edit box is used to specify additional properties of the tracks to be projected, such as 'Color', 'b'. Character vector entries must be enclosed in quotes.

Pressing the **Apply** button accepts the input data and displays the tracks on the current map axes.

Pressing the **Cancel** button disregards any input data and closes the Define Tracks dialog box.



Define Range Units Dialog Box

This dialog box, available only for one-point mode, allows for modification of the range units and the normalizing geoid.

The **Range Units** pull-down menu is used to select the units of the track range. The unit selected is displayed near the top of the Define Tracks dialog box, and all latitude and longitude entries must be entered in these units. Users must also be sure to specify the normalizing geoid in the same units. If radians are selected, it is assumed the range entry is a multiple of the radius used to display the current map.

The **Normalizing Geoid** edit box is used to modify the radius used to normalize range entries to radian values, which is necessary for proper calculations and map display. This entry must be in the same units as the range units. If the range units are in radians, then the normalizing geoid must be the same as the geoid used for the current map axes.

Pressing the **Cancel** button disregards any modifications and closes the Define Range Units dialog box.

Pressing the **Apply** button accepts any modifications and returns to the Define Tracks dialog box.

See Also

track1 | track2

Introduced before R2006a

uimaptbx

Handle buttondown callbacks for mapped objects

Activation

set the ButtonDownFcn property to 'uimaptbx'

Description

uimaptbx processes mouse events for mapped objects. uimaptbx can be assigned to an object by setting the ButtonDownFcn to 'uimaptbx'. This is the default setting for all objects created with Mapping Toolbox functions.

If uimaptbx is assigned to an object, the following mouse events are recognized: A single-click and hold on an object displays the object tag. If no tag is assigned, the object type is displayed. A double-click on an object activates the MATLAB Property Editor. An extend-click on an object activates the Projection Control dialog box, which allows the map projection and display properties to be edited. An alternate-click on an object allows basic properties to be edited using simple mouse clicks and drags.

Definitions of extend-click and alternate-click on various platforms are as follows:

For MS-Windows: Extend-click - **Shift**+click left button or both buttons

 Alternate-click - **Ctrl**+click left button or right button

For X-Windows: Extend-click - **Shift**+click left button or middle button

 Alternate-click - **Ctrl**+ click left button or right button

See Also

axesm | axesmui | property editors

Introduced before R2006a

utmzoneui

Choose or identify UTM zone by clicking map

Activation

| Command Line |
|---------------------|
| utmzoneui |
| utmzoneui(InitZone) |

Description


zone = utmzoneui opens an graphical user interface for choosing a UTM zone on a world display map. You select a zone by clicking an area for its appropriate zone, or entering a valid zone to identify the zone on the map.

zone = utmzoneui(InitZone) initialize the map displayed to the zone character vector specified in InitZone.

To interactively pick a UTM zone, activate the interface, and then click any rectangular zone on the world map to display its UTM zone. The selected zone is highlighted in red and its designation is displayed in the **Zone** edit field. Alternatively, type a valid UTM designation in the **Zone** edit field to select and see the location of a zone. Valid zone designations consist of an integer from 1 to 60 followed by a letter from C to X.

Typing only the numeric portion of a zone designation will highlight a column of cells. Clicking **Accept** returns a that UTM column designation. You cannot return a letter (row designation) in such a manner, however.

Controls



Tips

The syntax of `utmzoneui` is similar to that of `utmzone`. If `utmzone` is called with no arguments, the `utmzoneui` interface is displayed for you to select a zone. Note that `utmzone` can return latitude-longitude coordinates of a specified zone, but that `utmzoneui` only returns zone names.

See Also

`utmgeoid` | `utmzone`

Topics

Universal Polar Stereographic System
Universal Transverse Mercator System

Introduced before R2006a

vmap0ui

UI for selecting data from Vector Map Level 0


Description

`vmap0ui(dirname)` launches a graphical user interface for interactively selecting and importing data from a Vector Map Level 0 (VMAPO) data base. `dirname` is a character vector that specifies the folder containing the data base. For more on using `vmap0ui`, click the **Help** button after the interface appears.

`vmap0ui(devicename)` or `vmap0ui devicename` uses the logical device (volume) name specified in the character vector `devicename` to locate CD-ROM drive containing the VMAPO CD-ROM. Under the Windows operating system it could be 'F:', 'G:', or some other letter. Under Macintosh OS X it should be '/Volumes/VMAP'. Under other UNIX systems it could be '/cdrom/'.

`vmap0ui` can be used on Windows without any arguments. In this case it attempts to automatically detect a drive containing a VMAPO CD-ROM. If `vmap0ui` fails to locate the CD-ROM device, then specify it explicitly.

Controls



The `vmap0ui` screen lets you read data from the Vector Map Level 0 (VMAP0). The VMAP0 is the most detailed world map database available to the public.

You use the list to select the type of data and the map to select the region of interest. When you click the **Get** button, data is extracted and displayed on the map. Use the **Save** button to save the data in a MAT-file or to the base workspace for later display. The **Close** button closes the window.

The Map

The **Map** controls the geographic extent of the data to be extracted. `vmap0ui` extracts data for areas currently visible on the map. Use the mouse to zoom in or out to the area of interest. Type `help zoom` for more on zooming.

The VMAP0 divides the world into tiles of about 5-by-5 degrees. When extracting, data is returned for all visible tiles, including those parts of the tile that are outside the current

view. The map shows the VMAP0 tiles in light yellow with light gray edges. The data density is high, so extracting data for a large number of tiles can take much time and memory. A count of the number of visible tiles is above the map.

The List

The **List** controls the type of data to be extracted. The tree structure of the list reflects the structure of the VMAP0 database. Upon starting `vmap0ui`, the list shows the major categories of VMAP data, called themes. Themes are subdivided into features, which consist of data of common graphic types (patch, line, point, or text) or cultural types (airport, roads, railroads). Double-click a theme to see the associated features. Features can have properties and values, for example, a railroad tracks property, with values single or multiple. Double-click a feature to see the associated properties and values. Double-clicking an open theme or feature closes it. When a theme is selected, `vmap0ui` gets all the associated features. When a feature is selected, `vmap0ui` gets all of that feature's data. When properties and values are selected, `vmap0ui` gets the data for any of the properties and values that match (that is, the union operation).

The Get Button

The **Get** button reads the currently selected VMAP0 data and displays it on the map. Use the **Cancel** button on the progress bar to interrupt the process. For a quicker response, press the standard interrupt key combination for your platform.

The Clear Button

The **Clear** button removes any previously read data from the map.

The Save Button

The **Save** button saves the currently displayed VMAP0 data to a MAT-file or the base workspace. If you choose to save to a file, you are prompted for a filename and location. If you choose to save to the base workspace, you are notified of the variable names that will be overwritten.

Data are returned as Mapping Toolbox display structures with variable names based on theme and feature names. You can update vector display structures to geographic data structures. For information about display structure format, see “Version 1 Display

Structures” on page 1-257 in the reference page for `displaym`. The `updategeostruct` function performs such conversions.

Use `load` and `displaym` to redisplay the data from a file on a map axes. You can also use the `mlayers` GUI to read and display the data from a file. To display the data in the base workspace, use `displaym`. To display all the display structures, use `rootlayr; displaym(ans)`. To display all of the display structures using the `mlayers` GUI, type `rootlayr; mlayers(ans)`.

The Close Button

The **Close** button closes the `vmap0ui` panel.

Examples

- 1 Launch `vmap0ui` and automatically detect a CD-ROM on Microsoft Windows:

```
vmap0ui
```

- 2 Launch `vmap0ui` on Macintosh OS X (need to specify volume name):

```
vmap0ui('Volumes/VMAP')
```

See also

`displaym`, `extractm`, `mlayers`, `vmap0data`

Introduced before R2006a

zdatam-ui

GUI to adjust z-plane of mapped objects

Activation

| Command Line |
|----------------------|
| zdatam |
| zdatam(h) |
| zdatam(<i>str</i>) |

Description

zdatam brings up a Select Object dialog box for selecting mapped objects and adjusting their ZData property. Upon selecting the objects, the Specify Zdata dialog box is activated, in which the new ZData variable is entered. Note that not all mapped objects have the ZData property (for example text objects).

zdatam(h) activates the Specify Zdata dialog box for the objects specified by the handle h.


zdatam(*str*) activates the Specify Zdata dialog box for the objects identified by *str*, where *str* is any of the character vectors recognized by handlem.

Controls



Select Object Dialog Box

The scroll box is used to select the desired objects from the list of mapped objects. Pushing the **Select all** button highlights all objects in the scroll box for selection. Pushing the **OK** button activates another Specify Zdata dialog box. Pushing the **Cancel** button aborts the operation without changing any properties of the selected objects.



Specify ZData Dialog Box

The **Zdata Variable** edit box is used to specify the name of the ZData variable. Pressing the **List** button produces a list of all current workspace variables, from which the ZData variable can be selected. A scalar value or a valid MATLAB expression can also be entered. Pressing the **Apply** button changes the ZData property of all selected objects to the new values. Pressing the **Cancel** button closes the Specify ZData dialog box without changing the ZData property of the selected objects.

See Also

zdatam

Introduced in R2007a