F04QAF - NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

F04QAF solves sparse nonsymmetric equations, sparse linear least-squares problems and sparse damped linear least-squares problems, using a Lanczos algorithm.

2 Specification

SUBROUTINE FO4QAF(M, N, B, X, SE, APROD, DAMP, ATOL, BTOL, CONLIM, ITNLIM, MSGLVL, ITN, ANORM, ACOND, RNORM, 2 ARNORM, XNORM, WORK, RWORK, LRWORK, IWORK, 3 LIWORK, INFORM, IFAIL) INTEGER M, N, ITNLIM, MSGLVL, ITN, LRWORK, IWORK (LIWORK), LIWORK, INFORM, IFAIL 1 B(M), X(N), SE(N), DAMP, ATOL, BTOL, CONLIM, realANORM, ACOND, RNORM, ARNORM, XNORM, WORK (2*N), 1 2 RWORK (LRWORK) EXTERNAL APROD

3 Description

F04QAF can be used to solve a system of linear equations

$$Ax = b \tag{1}$$

where A is an n by n sparse nonsymmetric matrix, or can be used to solve linear least-squares problems, so that F04QAF minimizes the value ρ given by

$$\rho = ||r||, \quad r = b - Ax \tag{2}$$

where A is an m by n sparse matrix and ||r|| denotes the Euclidean length of r so that $||r||^2 = r^T r$. A damping parameter, λ , may be included in the least-squares problem in which case F04QAF minimizes the value ρ given by

$$\rho^2 = ||r||^2 + \lambda^2 ||x||^2 \tag{3}$$

 λ is supplied as the parameter DAMP and should of course be zero if the solution to problems (1) or (2) is required. Minimizing ρ in (3) is often called ridge regression.

F04QAF is based upon algorithm LSQR (see Paige and Saunders [1] pp 43–71 and [2] pp 195–209) and solves the problems by an algorithm based upon the Lanczos process. Details of the method are given in [1]. The routine does not require A explicitly, but A is specified via a user-supplied routine APROD which must perform the operations (y + Ax) and $(x + A^Ty)$ for a given n element vector x and x0 element vector y1. A parameter to APROD specifies which of the two operations is required on a given entry.

The routine also returns estimates of the standard errors of the sample regression coefficients $(x_i, \text{ for } i=1,2,\ldots,n)$ given by the diagonal elements of the estimated variance-covariance matrix V. When problem (2) is being solved and A is of full rank, then V is given by

$$V = s^2 (A^T A)^{-1}, \ s^2 = \rho^2 / (m - n), \ m > n$$

and when problem (3) is being solved then V is given by

$$V = s^2 (A^T A + \lambda^2 I)^{-1}, \ s^2 = \rho^2 / m, \ \lambda \neq 0.$$

Let \bar{A} denote the matrix

$$\bar{A} = A, \ \lambda = 0 \ ; \ \bar{A} = \begin{pmatrix} A \\ \lambda I \end{pmatrix}, \ \lambda \neq 0,$$
 (4)

let \bar{r} denote the residual vector

$$\bar{r} = r, \ \lambda = 0 \ ; \ \bar{r} = \begin{pmatrix} b \\ 0 \end{pmatrix} - \bar{A}x, \ \lambda \neq 0$$
 (5)

corresponding to an iterate x, so that $\rho = \|\bar{r}\|$ is the function being minimized, and let $\|A\|$ denote the Frobenius (Euclidean) norm of A. Then the routine accepts x as a solution if it is estimated that one of the following two conditions is satisfied:

$$\rho \le tol_1 \|\bar{A}\| \cdot \|x\| + tol_2 \|b\| \tag{6}$$

$$\|\bar{A}^T \bar{r}\| \le tol_1 \|\bar{A}\| \rho \tag{7}$$

where tol_1 and tol_2 are user-supplied tolerances which estimate the relative errors in A and b respectively. Condition (6) is appropriate for compatible problems where, in theory, we expect the residual to be zero and will be satisfied by an acceptable solution x to a compatible problem. Condition (7) is appropriate for incompatible systems where we do not expect the residual to be zero and is based upon the observation that, in theory,

$$\bar{A}^T \bar{r} = 0$$

when x is a solution to the least-squares problem, and so (7) will be satisfied by an acceptable solution x to a linear least-squares problem.

The routine also includes a test to prevent convergence to solutions, x, with unacceptably large elements. This can happen if A is nearly singular or is nearly rank deficient. If we let the singular values of \bar{A} be

$$\sigma_1 \ge \sigma_2 \ge \ldots \ge \sigma_n \ge 0$$

then the condition number of \bar{A} is defined as

$$\operatorname{cond}(\bar{A}) = \sigma_1/\sigma_k$$

where σ_k is the smallest non-zero singular value of \bar{A} and hence k is the rank of \bar{A} . When k < n, then \bar{A} is rank deficient, the least-squares solution is not unique and F04QAF will normally converge to the minimal length solution. In practice \bar{A} will not have exactly zero singular values, but may instead have small singular values that we wish to regard as zero.

The routine provides for this possibility by terminating if

$$\operatorname{cond}(\bar{A}) \ge c_{\lim} \tag{8}$$

where c_{lim} is a user-supplied limit on the condition number of \bar{A} . For problem (1) termination with this condition indicates that A is nearly singular and for problem (2) indicates that A is nearly rank deficient and so has near linear dependencies in its columns. In this case inspection of ||r||, $||A^Tr||$ and ||x||, which are all returned by the routine, will indicate whether or not an acceptable solution has been found. Condition (8), perhaps in conjunction with $\lambda \neq 0$, can be used to try and 'regularise' least-squares solutions. A full discussion of the stopping criteria is given in Section 6 of reference Paige and Saunders [1].

Introduction of a non-zero damping parameter λ tends to reduce the size of the computed solution and to make its components less sensitive to changes in the data, and F04QAF is applicable when a value of λ is known a priori. To have an effect, λ should normally be at least $\sqrt{\epsilon}||A||$ where ϵ is the **machine precision**. For further discussion see Paige and Saunders [2] and the references given there.

Whenever possible the matrix A should be scaled so that the relative errors in the elements of A are all of comparable size. Such a scaling helps to prevent the least-squares problem from being unnecessarily sensitive to data errors and will normally reduce the number of iterations required. At the very least, in the absence of better information, the columns of A should be scaled to have roughly equal column length.

4 References

[1] Paige C C and Saunders M A (1982) LSQR: An algorithm for sparse linear equations and sparse least-squares ACM Trans. Math. Software 8 43–71

F04QAF.2 [NP3390/19/pdf]

[2] Paige C C and Saunders M A (1982) Algorithm 583 LSQR: Sparse linear equations and least-squares problems ACM Trans. Math. Software 8 195–209

5 Parameters

1: M — INTEGER

On entry: m, the number of rows of the matrix A.

Constraint: $M \ge 1$.

2: N — INTEGER

On entry: n, the number of columns of the matrix A.

Constraint: $N \ge 1$.

3: B(M) - real array

Input/Output

On entry: the right-hand side vector b.

On exit: the array is overwritten.

4: X(N) — real array

On exit: the solution vector x.

5: $SE(N) - real \operatorname{array}$

Output

Output

On exit: the estimates of the standard errors of the components of x. Thus SE(i) contains an estimate of the element v_{ii} of the estimated variance-covariance matrix V. The estimates returned in SE will be the lower bounds on the actual estimated standard errors, but will usually have at least one correct figure.

6: APROD — SUBROUTINE, supplied by the user.

External Procedure

APROD must perform the operations y := y + Ax and $x := x + A^Ty$ for given vectors x and y. Its specification is:

SUBROUTINE APROD(MODE, M, N, X, Y, RWORK, LRWORK, IWORK, LIWORK)
INTEGER MODE, M, N, LRWORK, IWORK(LIWORK), LIWORK

real X(N), Y(M), RWORK(LRWORK)

1: MODE — INTEGER

Input/Output

On entry: MODE specifies which operation is to be performed:

If MODE = 1, then APROD must compute y + Ax.

If MODE = 2, then APROD must compute $x + A^T y$.

On exit: MODE may be used as a flag to indicate a failure in the computation of y+Ax or $x+A^{T}y$. If MODE is negative on exit from APROD, F04QAF will exit immediately with IFAIL set to MODE.

2: M — INTEGER

Input

On entry: m, the number of rows of A.

3: N — INTEGER

Input

On entry: n, the number of columns of A.

4: X(N) - real array

Input/Output

On entry: the vector x.

On exit: if MODE = 1, X must be unchanged;

If MODE = 2, X must contain $x + A^T y$.

5: Y(M) - real array

Input/Output

On entry: the vector y.

On exit: if MODE = 1, Y must contain y + Ax;

If MODE = 2, Y must be unchanged.

6: RWORK(LRWORK) — real array

User Workspace

7: LRWORK — INTEGER

Input

8: IWORK(LIWORK) — INTEGER array

User Workspace

9: LIWORK — INTÉGER

Input

APROD is called from F04QAF with the parameters RWORK, LRWORK, IWORK and LIWORK as supplied to F04QAF. The user is free to use the arrays RWORK and IWORK to supply information to APROD as an alternative to using COMMON.

APROD must be declared as EXTERNAL in the (sub)program from which F04QAF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

7: DAMP — real

Innut

On entry: the value λ . If either problem (1) or problem (2) is to be solved, then DAMP must be supplied as zero.

8: ATOL — real

Input

On entry: the tolerance, tol_1 , of the convergence criteria (6) and (7); it should be an estimate of the largest relative error in the elements of A. For example, if the elements of A are correct to about 4 significant figures, then ATOL should be set to about 5×10^{-4} . If ATOL is supplied as less than ϵ , where ϵ is the **machine precision**, then the value ϵ is used in place of ATOL.

9: BTOL — real

Input

On entry: the tolerance, tol_2 , of the convergence criterion (6); it should be an estimate of the largest relative error in the elements of B. For example, if the elements of B are correct to about 4 significant figures, then BTOL should be set to about 5×10^{-4} . If BTOL is supplied as less than ϵ , where ϵ is the **machine precision**, then the value ϵ is used in place of BTOL.

10: CONLIM — real

Input

On entry: the value c_{lim} of equation (8); it should be an upper limit on the condition number of \bar{A} . CONLIM should not normally be chosen much larger than 1.0/ATOL. If CONLIM is supplied as zero then the value $1.0/\epsilon$, where ϵ is the **machine precision**, is used in place of CONLIM.

11: ITNLIM — INTEGER

Input

On entry: an upper limit on the number of iterations. If ITNLIM ≤ 0 , then the value N is used in place of ITNLIM, but for ill-conditioned problems a higher value of ITNLIM is likely to be necessary.

12: MSGLVL — INTEGER

Innut

On entry: the level of printing from F04QAF. If MSGLVL \leq 0, then no printing occurs, but otherwise messages will be output on the advisory message channel (see X04ABF). A description of the printed output is given in Section 5.1 below. The level of printing is determined as follows:

 $MSGLVL \le 0$

No printing.

MSGLVL = 1

A brief summary is printed just prior to return from F04QAF.

MSGLVL > 2

A summary line is printed periodically to monitor the progress of F04QAF, together with a brief summary just prior to return from F04QAF.

F04QAF.4 [NP3390/19/pdf]

Output

13: ITN — INTEGER

On exit: the number of iterations performed.

14: ANORM — real

On exit: an estimate of $||\bar{A}||$ for the matrix \bar{A} of equation (4).

15: ACOND - real

On exit: an estimate of $cond(\bar{A})$ which is a lower bound.

16: RNORM — real Output

On exit: an estimate of $\|\bar{r}\|$ for the residual, \bar{r} , of equation (5) corresponding to the solution x returned in X. Note that $\|\bar{r}\|$ is the function being minimized.

17: ARNORM — real

On exit: an estimate of the $\|\bar{A}^T\bar{r}\|$ corresponding to the solution x returned in X.

18: XNORM - real

On exit: an estimate of ||x|| for the solution x returned in X.

19: WORK(2*N) — real array

Work space

20: RWORK(LRWORK) — *real* array

User Workspace

RWORK is not used by F04QAF, but is passed directly to routine APROD and may be used to pass information to that routine.

21: LRWORK — INTEGER

Inpu

On entry: the length of the array RWORK as declared in the (sub)program from which F04QAF is called.

Constraint: LRWORK ≥ 1 .

22: IWORK(LIWORK) — INTEGER array

 $User\ Workspace$

IWORK is not used by F04QAF, but is passed directly to routine APROD and may be used to pass information to that routine.

23: LIWORK — INTEGER

Input

On entry: the length of the array IWORK as declared in the (sub)program from which F04QAF is called.

Constraint: LIWORK ≥ 1 .

24: INFORM — INTEGER

Output

On exit: the reason for termination of F04QAF as follows:

INFORM = 0

The exact solution is x = 0. No iterations are performed in this case.

INFORM = 1

The termination criterion of equation (6) has been satisfied with tol_1 and tol_2 as the values supplied in ATOL and BTOL respectively.

INFORM = 2

The termination criterion of equation (7) has been satisfied with tol_1 as the value supplied in ATOL.

INFORM = 3

The termination criterion of equation (6) has been satisfied with tol_1 and/or tol_2 as the value ϵ , where ϵ is the **machine precision**. One or both of the values supplied in ATOL and BTOL must have been less than ϵ and was too small for this machine.

INFORM = 4

The termination criterion of equation (7) has been satisfied with tol_1 as the value ϵ , where ϵ is the **machine precision**. The value supplied in ATOL must have been less than ϵ and was too small for this machine.

The values INFORM = 5, INFORM = 6 and INFORM = 7 correspond to failure with IFAIL = 2, IFAIL = 3 and IFAIL = 4 respectively (see Section 6) and when IFAIL is negative INFORM will be set to the same negative value.

25: IFAIL — INTEGER Input/Output

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

5.1 Description of the printed output

When MSGLVL > 0, then F04QAF will produce output (except in the case where the routine fails with IFAIL = 1) on the advisory message channel (see X04ABF).

When MSGLVL ≥ 2 then a summary line is printed periodically giving the following information:

Output	Meaning
ITN	Iteration number, k .
X(1)	The first element of the current iterate x_k .
FUNCTION	The current value of the function, ρ , being minimized.
COMPAT	An estimate of $\ \bar{r}_k\ /\ b\ $, where \bar{r}_k is the residual corresponding to x_k . This
	value should converge to zero (in theory) if and only if the problem is compatible.
	COMPAT decreases monotonically.
INCOMPAT	An estimate of $\ \bar{A}^T\bar{r}_k\ /(\ \bar{A}\ \ \bar{r}_k\)$ which should converge to zero if and only if at
	the solution ρ is non-zero. INCOMPAT is not usually monotonic.
NRM(ABAR)	A monotonically increasing estimate of $\ \bar{A}\ $.
COND(ABAR)	A monotonically increasing estimate of the condition number $\operatorname{cond}(\bar{A})$.

6 Error Indicators and Warnings

Errors detected by the routine:

```
IFAIL < 0
```

A negative value of IFAIL indicates an exit from F04QAF because the user has set MODE negative in APROD. The value of IFAIL will be the same as the user's setting of MODE.

IFAIL = 1

```
On entry, M < 1, or N < 1, or LRWORK < 1, or LIWORK < 1.
```

IFAIL = 2

The condition of equation (8) has been satisfied for the value of $c_{\rm lim}$ supplied in CONLIM. If this failure is unexpected the user should check that APROD is working correctly. Although conditions (6) or (7) have not been satisfied, the values returned in RNORM, ARNORM and XNORM may nevertheless indicate that an acceptable solution has been reached.

IFAIL = 3

The conditions of equation (8) has been satisfied for the value $c_{\text{lim}} = 1.0/\epsilon$, where ϵ is the **machine precision**. The matrix \bar{A} is nearly singular or rank deficient and the problem is too ill-conditioned for this machine. If this failure is unexpected, the user should check that APROD is working correctly.

F04QAF.6 [NP3390/19/pdf]

IFAIL = 4

The limit on the number of iterations has been reached. The number of iterations required by F04QAF and the condition of the matrix \bar{A} can depend strongly on the scaling of the problem. Poor scaling of the rows and columns of A should be avoided whenever possible.

7 Accuracy

When the problem is compatible, the computed solution x will satisfy the equation

$$r = b - Ax$$

where an estimate of ||r|| is returned in the parameter RNORM. When the problem is incompatible, the computed solution x will satisfy the equation

$$\bar{A}^T \bar{r} = e$$
,

where an estimate of ||e|| is returned in the parameter ARNORM. See also Section 6.2 of Paige and Saunders [2] pp 43–71.

8 Further Comments

The time taken by the routine is likely to be principally determined by the time taken in APROD, which is called twice on each iteration, once with MODE = 1 and once with MODE = 2. The time taken per iteration by the remaining operations in F04QAF is approximately proportional to $\max(m, n)$.

The Lanczos process will usually converge more quickly if A is pre-conditioned by a non-singular matrix M that approximates A in some sense and is also chosen so that equations of the form My = c can efficiently be solved for y. Some discussion of pre-conditioning in the context of symmetric matrices is given in F04MBF. In the context of F04QAF, problem (1) is equivalent to

$$(AM^{-1})y = b$$
, $Mx = y$

and problem (2) is equivalent to minimizing

$$\rho = ||r||, \quad r = b - (AM^{-1})y, \quad Mx = y.$$

Note that the normal matrix $(AM^{-1})^T(AM^{-1}) = M^{-T}(A^TA)M^{-1}$ so that the pre-conditioning AM^{-1} is equivalent to the pre-conditioning $M^{-T}(A^TA)M^{-1}$ of the normal matrix A^TA .

Pre-conditioning can be incorporated into F04QAF simply by coding the routine APROD to compute $y + AM^{-1}x$ and $x + M^{-T}A^{T}y$ in place of y + Ax and $x + A^{T}y$ respectively, and then solving the equations Mx = y for x on return from F04QAF. $y + AM^{-1}x$ should be computed by solving Mz = x for z and then computing y + Az, and $x + M^{-T}A^{T}y$ should be computed by solving $M^{T}z = A^{T}y$ for z and then forming x + z.

9 Example

To solve the linear least-squares problem

minimize
$$\rho = ||r||, \quad r = b - Ax$$

where A is the 13 by 12 matrix and b is the 13 element vector given by

with h = 0.1.

Such a problem can arise by considering the Neumann problem on a rectangle

$$\frac{\delta u}{\delta n} = 0$$

$$\frac{\delta u}{\delta n} = 0 \quad \nabla^2 u = g(x, y) \quad \frac{\delta u}{\delta n} = 0 \quad \int_c u = 1$$

$$\frac{\delta u}{\delta n} = 0$$

where C is the boundary of the rectangle, and discretising as illustrated below with the square mesh




Figure 1

The 12 by 12 symmetric part of A represents the difference equations and the final row comes from the normalising condition. The example program has g(x,y) = 1 at all the internal mesh points, but apart from this is written in a general manner so that the number of rows (NROWS) and columns (NCOLS) in the grid can readily be altered.

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

* F04QAF Example Program Text

* Mark 14 Revised. NAG Copyright 1989.

* .. Parameters ..

INTEGER MMAX, NMAX, LIWORK, LRWORK

PARAMETER (MMAX=100,NMAX=99,LIWORK=1,LRWORK=1)

INTEGER NOUT
PARAMETER (NOUT=6)

* .. Scalars in Common ..

INTEGER NCOLS, NROWS

```
.. Local Scalars ..
  real
                    ACOND, ANORM, ARNORM, ATOL, BTOL, C, CONLIM,
                    DAMP, H, RNORM, XNORM
                    I, I1, IFAIL, INFORM, ITN, ITNLIM, K, M, MSGLVL,
  INTEGER
   .. Local Arrays ..
                    B(MMAX), RWORK(LRWORK), SE(NMAX), WORK(NMAX,2),
  real
                    X(NMAX)
  INTEGER
                   IWORK(LIWORK)
  .. External Subroutines ..
  EXTERNAL
                   APROD, FO4QAF, XO4ABF
   .. Common blocks ..
  COMMON
                    /USER/NROWS, NCOLS
   .. Executable Statements ..
  WRITE (NOUT,*) 'FO4QAF Example Program Results'
  WRITE (NOUT,*)
  CALL XO4ABF(1,NOUT)
  NROWS = 4
  NCOLS = 4
  H = 0.1e0
  N = NCOLS*NROWS - 4
  M = N + 1
  IF (NROWS.LT.3 .OR. NCOLS.LT.3 .OR. M.GT.MMAX) THEN
      WRITE (NOUT,99998) 'NROWS or NCOLS is out of range: NROWS = ',
        NROWS, ' NCOLS = ', NCOLS
  ELSE
      Initialize RHS and other quantities required by F04QAF.
      Convergence will be sooner if we do not regard A as exact,
      so ATOL is not set to zero.
      DO 20 I = 1, N
        B(I) = 0.0e0
20
      CONTINUE
      C = -H**2
      I1 = NROWS
      DO 60 K = 3, NCOLS
         DO 40 I = I1, I1 + NROWS - 3
            B(I) = C
40
         CONTINUE
         I1 = I1 + NROWS
60
      CONTINUE
      B(M) = 1.0e0/H
      DAMP = 0.0e0
      ATOL = 1.0e-5
      BTOL = 1.0e-4
      CONLIM = 1.0eO/ATOL
      ITNLIM = 100
      * Set MSGLVL to 2 to get output at each iteration *
      MSGLVL = 1
      IFAIL = 1
      CALL FO4QAF(M,N,B,X,SE,APROD,DAMP,ATOL,BTOL,CONLIM,ITNLIM,
                  MSGLVL, ITN, ANORM, ACOND, RNORM, ARNORM, XNORM, WORK,
                  RWORK, LRWORK, IWORK, LIWORK, INFORM, IFAIL)
      WRITE (NOUT,*)
      IF (IFAIL.NE.O) THEN
```

```
WRITE (NOUT, 99999) 'FO4QAF fails. IFAIL =', IFAIL
         ELSE
            WRITE (NOUT,*) 'Solution returned by FO4QAF'
            WRITE (NOUT, 99997) (X(I), I=1, N)
            WRITE (NOUT, *)
            WRITE (NOUT, 99996) 'Norm of the residual = ', RNORM
         END IF
      END IF
      STOP
99999 FORMAT (1X,A,I3)
99998 FORMAT (1X,A,16,A,16)
99997 FORMAT (1X,5F9.3)
99996 FORMAT (1X,A,1P,e12.2)
      END
      SUBROUTINE APROD (MODE, M, N, X, Y, RWORK, LRWORK, IWORK, LIWORK)
      APROD returns
        Y = Y + A*X
                              when MODE = 1
        X = X + (A**T)*Y when MODE = 2
      for a given X and Y.
      .. Scalar Arguments ..
                       LIWORK, LRWORK, M, MODE, N
      INTEGER
      .. Array Arguments ..
      real
                      RWORK(LRWORK), X(N), Y(M)
      INTEGER
                      IWORK(LIWORK)
      .. Scalars in Common ..
      INTEGER NCOLS, NROWS
      .. Local Scalars ..
      INTEGER
                      J, J1, J2
      .. External Subroutines ..
      EXTERNAL ATIMES
      .. Common blocks ..
      COMMON
                      /USER/NROWS, NCOLS
      .. Executable Statements ...
      IF (MODE.NE.2) THEN
         CALL ATIMES (NROWS, NCOLS, N, X, Y)
         DO 20 J = 1, NROWS -2
            Y(M) = Y(M) + X(J)
         CONTINUE
   20
         DO 40 J = 1, NCOLS - 2
            Y(M) = Y(M) + X(J*NROWS-1) + X(J*NROWS+NROWS-2)
   40
         CONTINUE
         DO 60 J = M - NROWS + 2, N
            Y(M) = Y(M) + X(J)
         CONTINUE
   60
      ELSE
         CALL ATIMES (NROWS, NCOLS, N, Y, X)
         DO 80 J = 1, NROWS - 2
            X(J) = X(J) + Y(M)
   80
         CONTINUE
         DO 100 J = 1, NCOLS - 2
            J1 = J*NROWS - 1
            J2 = J1 + NROWS - 1
            X(J1) = X(J1) + Y(M)
            X(J2) = X(J2) + Y(M)
  100
         CONTINUE
         DO 120 J = M - NROWS + 2, N
```

F04QAF.10 [NP3390/19/pdf]

```
X(J) = X(J) + Y(M)
120
      CONTINUE
   END IF
   RETURN
   END
   SUBROUTINE ATIMES (NROWS, NCOLS, N, X, Y)
   ATIMES is called by routine APROD and returns
      Y = Y + ANN*X,
   where ANN is the N by N symmetric part of the matrix A.
   .. Scalar Arguments ..
   INTEGER
                      N, NCOLS, NROWS
    .. Array Arguments ..
                      X(N), Y(N)
   real
   .. Local Scalars ..
   INTEGER
                     I, I1, I2, I3, IL, J
   .. Executable Statements ...
   DO 20 J = 1, NROWS - 2
      Y(J) = Y(J) + X(J) - X(J+NROWS-1)
20 CONTINUE
   DO 60 J = 1, NCOLS - 2
      I = J*NROWS - 1
      Y(I) = Y(I) + X(I) - X(I+1)
      I1 = I + 1
       IL = I1 + NROWS - 3
      DO 40 I = I1, IL
          I2 = I - NROWS
          IF (J.EQ.1) I2 = I2 + 1
          I3 = I + NROWS
          IF (J.EQ.NCOLS-2) I3 = I3 - 1
          Y(I) = Y(I) - X(I2) - X(I-1) + 4.0e0*X(I) - X(I+1) - X(I3)
40
      CONTINUE
      I = IL + 1
      Y(I) = Y(I) - X(I-1) + X(I)
60 CONTINUE
   DO 80 J = N - NROWS + 3, N
      Y(J) = Y(J) - X(J-NROWS+1) + X(J)
80 CONTINUE
   RETURN
   END
```

9.2 Program Data

None.

9.3 Program Results

```
FO4QAF Example Program Results
OUTPUT FROM FO4QAF.
LEAST-SQUARES SOLUTION OF A*X = B
                                   12 COLS
THE MATRIX A HAS
                   13 ROWS AND
THE DAMPING PARAMETER IS DAMP =
                                    0.00E+00
          1.00E-05
                     CONLIM =
ATOL =
                                    1.00E+05
BTOL =
          1.00E-04
                   ITNLIM =
                                  100
```

```
NO. OF ITERATIONS = 2
STOPPING CONDITION = 2
( THE LEAST-SQRS SOLN IS GOOD ENOUGH, GIVEN ATOL )

ACTUAL NORM( RBAR ), NORM( X ) 1.15E-02 4.33E+00
NORM( TRANSPOSE( ABAR )*RBAR ) 9.16E-15
ESTIMATES OF NORM( ABAR ), COND( ABAR ) 4.12E+00 2.45E+00

Solution returned by FO4QAF
1.250 1.250 1.250 1.247 1.247
1.250 1.250 1.250 1.247 1.250
1.250 1.250
```

Norm of the residual = 1.15E-02

F04QAF.12 (last) [NP3390/19/pdf]