G01AJF - NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

G01AJF prints a histogram on a character printing device, with user control over size, positioning, and the range of data values included.

2 Specification

```
SUBROUTINE GO1AJF(X, N, NSTEPX, NSTEPY, ITYPE, ISPACE, XMIN, XMAX,

XSTEP, N1, MULTY, IFAIL)

INTEGER

N, NSTEPX, NSTEPY, ITYPE, ISPACE, N1, MULTY,

IFAIL

real

X(N), XMIN, XMAX, XSTEP
```

3 Description

A histogram is printed using vertical bars consisting of * characters. The output is directed to the current advisory message unit (see the Users' Note for your implementation). It may be redirected by a call to X04ABF before calling G01AJF.

The following options are available:

- (a) Inclusion of all data values, or only of those lying within a specified range.
- (b) Specification of the size of the histogram in the vertical and horizontal directions; and of positioning in the horizontal direction.
- (c) Calculation of frequencies or cumulative frequencies in the histogram.

The maximum and minimum data values used, the (integral) number of observations represented by each * in the histogram, and the step size per character position in the horizontal direction, are returned.

The histogram is headed FREQUENCY or CUM.FREQ. depending on the option selected. Each line is annotated with the minimum frequency which a bar reaching that line represents. The data maximum and minimum are printed under the histogram, unless either exceeds 9999.99 in modulus, in which case they are not printed (although they are still returned).

4 References

None.

5 Parameters

```
1: X(N) — real array

On entry: the data values.
```

2: N — INTEGER

On entry: the number of data values.

Constraint: $N \geq 1$.

3: NSTEPX — INTEGER

Input/Output

On entry: the number of character positions to be used in the horizontal direction, i.e., the number of categories in the histogram.

[NP3390/19/pdf] G01AJF.1

On exit: if NSTEPX < 10 on entry, NSTEPX is reset to 10.

If NSTEPX > 99 on entry, NSTEPX is reset to 99.

Otherwise, NSTEPX is unchanged on exit.

4: NSTEPY — INTEGER

Input/Output

On entry: the number of character positions to be used in the vertical direction, i.e., the maximum height of a histogram bar.

On exit: if NSTEPY < 10 on entry, NSTEPY is reset to 10.

If NSTEPY > 99 on entry, NSTEPY is reset to 99.

Otherwise, NSTEPY is unchanged on exit.

5: ITYPE — INTEGER

Input

On entry: indicates whether a histogram of frequencies or cumulative frequencies is required.

ITYPE = 0 for frequencies.

ITYPE $\neq 0$ for cumulative frequencies.

The second option effectively displays the distribution function of the data rather than the density function.

6: ISPACE — INTEGER

Input

On entry: indicates how many spaces are to be inserted at the beginning of each output line.

If ISPACE < 0 on input, ISPACE = 0 is used

If ISPACE + NSTEPX + 14 > 120, then ISPACE = 0 is used.

The second condition imposes an effective line length limit of 120 characters.

7: XMIN - real

Input/Output

8: XMAX - real

Input/Output

On entry: if XMIN < XMAX, only those values in X such that XMIN \leq X(i) \leq XMAX, for i = 1, 2, ..., n, are included in the histogram.

If XMIN \geq XMAX, all the data are included.

On exit: if XMIN < XMAX on entry, then XMIN and XMAX are unchanged.

If XMIN \geq XMAX then XMIN and XMAX contain the minimum and maximum data values respectively.

9: XSTEP — real

Output

On exit: the width of each class interval.

10: N1 — INTEGER

Output

On exit: the total number of observations actually included in the histogram.

11: MULTY — INTEGER

Output

On exit: the number of observations represented by each * in the histogram.

12: IFAIL — INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

G01AJF.2 [NP3390/19/pdf]

6 Error Indicators and Warnings

Errors detected by the routine:

```
\begin{aligned} \text{IFAIL} &= 1 \\ \text{On entry,} \quad \text{N} &< 1. \end{aligned}
```

7 Accuracy

Accuracy is limited by the number of plotting positions available.

8 Further Comments

The time taken by the routine increases with N, NSTEPX and NSTEPY.

A total of (NSTEPX+ISPACE+14) character positions are used in the horizontal direction, not including the carriage control character. It is important that this total does not exceed the maximum line length available on the output device.

A total of (NSTEPY+3) output lines are normally generated, one less if XMIN and/or XMAX is too large in modulus to be printed.

9 Example

A sample of 50 random numbers (which were generated by G05DDF) form the data, which correspond to a Normal distribution with mean and standard deviation both equal to 5.0. A histogram of the entire sample is drawn first, followed by a cumulative histogram of all data values lying between -10.0 and 5.0. The first histogram is indented 10 character positions. Note the use of X04ABF to direct the output to unit number 6.

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
GO1AJF Example Program Text
Mark 14 Revised. NAG Copyright 1989.
.. Parameters ..
INTEGER
PARAMETER
                 (N=50)
INTEGER
                 NIN, NOUT
PARAMETER
                  (NIN=5, NOUT=6)
.. Local Scalars .
real
                 XMAX, XMIN, XSTEP
INTEGER
                 I, IFAIL, ISPACE, ITYPE, MULTY, N1, NSTEPX,
                 NSTEPY
.. Local Arrays ..
real
                 X(N)
.. External Subroutines ..
EXTERNAL
                 GO1AJF, XO4ABF
.. Executable Statements ..
WRITE (NOUT,*) 'GO1AJF Example Program Results'
Skip heading in data file
READ (NIN,*)
READ (NIN,*) (X(I),I=1,N)
WRITE (NOUT,*)
NSTEPX = 10
```

[NP3390/19/pdf] G01AJF.3

```
NSTEPY = 10
ITYPE = 0
ISPACE = 10
XMIN = 0.0e0
XMAX = 0.0e0
CALL XO4ABF(1,NOUT)
IFAIL = 0
CALL GO1AJF(X,N,NSTEPX,NSTEPY,ITYPE,ISPACE,XMIN,XMAX,XSTEP,N1,
            MULTY, IFAIL)
WRITE (NOUT,*)
WRITE (NOUT,*)
WRITE (NOUT, *)
ITYPE = 1
ISPACE = 0
XMIN = -10.0e0
XMAX = 5.0e0
IFAIL = 0
CALL GO1AJF(X,N,NSTEPX,NSTEPY,ITYPE,ISPACE,XMIN,XMAX,XSTEP,N1,
            MULTY, IFAIL)
STOP
END
```

9.2 Program Data

```
G01AJF Example Program Data

2.68 8.23 0.11 1.39 -2.77 -1.17 3.49 7.39 5.22 5.44

7.06 6.17 -4.44 5.98 14.02 8.06 10.96 0.99 7.87 4.85

9.76 3.30 4.45 7.02 5.43 3.57 1.98 3.09 -2.66 5.04

14.52 -0.61 5.04 6.85 3.94 4.87 3.82 5.93 7.89 9.48

6.81 6.91 7.76 6.21 0.55 -2.44 18.09 6.19 9.19 10.55
```

9.3 Program Results

GO1AJF Example Program Results

```
FREQUENCY
  20 .
                     20
  18
                     18
  16
                     16
  14
                     14
  12
                    12
  10
                    10
   8
                     8
   6
                     6
                     4
      .***** * .
     -4.44 18.09
```

G01AJF.4 [NP3390/19/pdf]

CUM. FI	REQ.		
30			30
27			27
24			24
21		*.	21
18		*.	18
15		**.	15
12		**.	12
9		***.	9
6		****.	6
3		*****.	3
-10.00		5.00	

 $[NP3390/19/pdf] \hspace{3cm} G01AJF.5 \hspace{0.1cm} (last)$