# NAG Fortran Library Routine Document G13BGF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

## 1 Purpose

G13BGF accepts a series of new observations of an output time series and any associated input time series, for which a multi-input model is already fully specified, and updates the 'state set' information for use in constructing further forecasts.

The previous specification of the multi-input model will normally have been obtained by using G13BEF to estimate the relevant transfer function and ARIMA parameters. The supplied state set will originally have been produced by G13BEF (or possibly G13BJF), but may since have been updated by G13BGF.

# 2 Specification

```
SUBROUTINE G13BGF(STTF, NSTTF, MR, NSER, MT, PARA, NPARA, NNV, XXYN,

IXXYN, KZEF, RES, WA, IWA, IFAIL)

INTEGER

NSTTF, MR(7), NSER, MT(4,NSER), NPARA, NNV, IXXYN,

KZEF, IWA, IFAIL

real

STTF(NSTTF), PARA(NPARA), XXYN(IXXYN,NSER), RES(NNV),

WA(IWA)
```

## 3 Description

The multi-input model is specified in Section 3 of the document for G13BEF. The form of these equations required to update the state set is as follows:

$$z_t = \delta_1 z_{t-1} + \delta_2 z_{t-2} + \dots + \delta_p z_{t-p} + \omega_0 x_{t-b} - \omega_1 x_{t-b-1} - \dots - \omega_q x_{t-b-q}$$

the transfer models which generate input component values  $z_{i,t}$  from one or more inputs  $x_{i,t}$ ,

$$n_t = y_t - z_{1,t} - z_{2,t} - \dots - z_{m,t}$$

which generates the output noise component from the output  $y_t$  and the input components, and

$$\begin{array}{ll} w_t &= \nabla^d \nabla^D_s n_t - c \\ e_t &= w_t - \varPhi_1 w_{t-s} - \varPhi_2 w_{t-2 \times s} - \dots - \varPhi_P w_{t-P \times s} + \varTheta_1 e_{t-s} + \varTheta_2 e_{t-2 \times s} + \dots + \varTheta_Q e_{t-Q \times s} \\ a_t &= e_t - \varPhi_1 e_{t-1} - \varPhi_2 e_{t-2} - \dots - \varPhi_P e_{t-p} + \varTheta_1 a_{t-1} + \varTheta_2 a_{t-2} + \dots + \varTheta_q a_{t-q} \end{array}$$

the ARIMA model for the output noise which generates the residuals  $a_t$ .

The state set (as also given in Section 3 of the document for G13BEF) is the collection of terms

$$z_{n+1-k}, x_{n+1-k}, n_{n+1-k}, w_{n+1-k}, e_{n+1-k}$$
 and  $a_{n+1-k}$ 

for k = 1 up to the maximum lag associated with each of these series respectively, in the above model equations. n is the latest time point of the series from which the state set has been generated.

The routine accepts further values of the series  $y_t$ ,  $x_{1,t}$ ,  $x_{2,t}$ , ...,  $x_{m,t}$  for t = n + 1, n + 2, ..., n + l, and applies the above model equations over this time range, to generate new values of the various model components, noise series and residuals. The state set is reconstructed, corresponding to the latest time point n + l, the earlier values being discarded.

The set of residuals corresponding to the new observations may be of use in checking that the new observations conform to the previously fitted model. The components of the new observations of the output series which are due to the various inputs, and the noise component, are also optionally returned.

The parameters of the model are not changed in this routine.

[NP3546/20A] G13BGF.1

## 4 References

Box G E P and Jenkins G M (1976) *Time Series Analysis: Forecasting and Control* (Revised Edition) Holden-Day

## 5 Parameters

#### 1: STTF(NSTTF) – *real* array

Input/Output

On entry: the NSTTF values in the state set before updating as returned by G13BEF, G13BJF or a previous call to G13BGF.

On exit: the state set values after updating.

#### 2: NSTTF - INTEGER

Input

On entry: the exact number of values in the state set array STTF as returned by G13BEF or G13BJF.

#### 3: MR(7) – INTEGER array

Input

On entry: the orders vector (p, d, q, P, D, Q, s) of the ARIMA model for the output noise component.

p, q, P and Q refer respectively to the number of autoregressive  $(\phi)$ , moving average  $(\theta)$ , seasonal autoregressive  $(\Phi)$  and seasonal moving average  $(\Theta)$  parameters.

d, D and s refer respectively to the order of non-seasonal differencing, the order of seasonal differencing, and the seasonal period.

#### 4: NSER – INTEGER

Input

On entry: the total number of input and output series. There may be any number of input series (including none), but only one output series.

## 5: MT(4,NSER) – INTEGER array

Input

On entry: the transfer function model orders b, p and q of each of the input series. The data for input series i are held in column i. Row 1 holds the value  $b_i$ , row 2 holds the value  $q_i$  and row 3 holds the value  $p_i$ . For a simple input,  $b_i = q_i = p_i = 0$ .

Row 4 holds the value  $r_i$ , where  $r_i = 1$  for a simple input and  $r_i = 2$  or 3 for a transfer function input. When  $r_i = 1$  any non-zero contents of rows 1, 2 and 3 of column i are ignored. The choice of  $r_i = 2$  or  $r_i = 3$  is an option for use in model estimation and does not affect the operation of this routine.

Constraint: MT(4, i) = 1,2 or 3 for i = 1, 2, ..., NSER - 1.

## 6: PARA(NPARA) – *real* array

Input

On entry: estimates of the multi-input model parameters as returned by G13BEF. These are in order, firstly the ARIMA model parameters: p values of  $\phi$  parameters, q values of  $\theta$  parameters and Q values of  $\Theta$  parameters. These are followed by the transfer function model parameter values  $\omega_0, \omega_1, \ldots, \omega_{q_1}, \delta_1, \delta_2, \ldots, \delta_{p_1}$  for the first of any input series and similarly for each subsequent input series. The final component of PARA is the value of the constant c.

#### 7: NPARA – INTEGER

Input

On entry: the exact number of  $\phi$ ,  $\theta$ ,  $\Phi$ ,  $\Theta$ ,  $\omega$ ,  $\delta$  and c parameters. (c must be included whether its value was previously estimated or was set fixed.)

G13BGF.2 [NP3546/20A]

## 8: NNV – INTEGER

Input

On entry: the number of new observation sets being used to update the state set, each observation set consisting of a value of the output series and the associated values of each of the input series at a particular time point.

#### 9: XXYN(IXXYN,NSER) – *real* array

Input/Output

On entry: the NNV new observation sets being used to update the state set. Column i contains the values of input series i. Column NSER contains the values of the output series. Consecutive rows correspond to increasing time sequence.

On exit: if KZEF = 0, XXYN remains unchanged.

If KZEF  $\neq$  0, the columns of XXYN hold the corresponding values of the input component series  $z_t$  and the output noise component  $n_t$ , in that order.

#### 10: IXXYN - INTEGER

Input

On entry: the first dimension of the array XXYN as declared in the (sub)program from which G13BGF is called.

Constraint:  $IXXYN \ge NNV$ .

#### 11: KZEF – INTEGER

Input

On entry: KZEF must not be set to 0, if the values of the input component series  $z_t$  and the values of the output noise component  $n_t$  are to overwrite the contents of XXYN on exit, and must be set to 0 if XXYN is to remain unchanged on exit.

## 12: RES(NNV) – *real* array

Output

On exit: the values of the residual series  $a_t$  corresponding to the new observations of the output series.

## 13: WA(IWA) - real array

Workspace

14: IWA – INTEGER

Input

On entry: the dimension of the array WA as declared in the (sub)program from which G13BGF is called.

Constraint: IWA  $\geq$  NNV + 2 × NSTTF + max(NNV, NSTTF) + max(NNV, ncc), where  $ncc = 4 \times (p + q + P + Q)$ .

## 15: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

# 6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, NSTTF is not consistent with the orders in arrays MR and MT.

[NP3546/20A] G13BGF.3

```
IFAIL = 2
```

On entry, NPARA is not consistent with the orders in arrays MR and MT.

```
IFAIL = 3
```

On entry, IXXYN is too small.

IFAIL = 4

On entry, IWA is too small.

IFAIL = 5

On entry, one of the  $r_i$ , stored in MT(4, i), for i = 1, 2, ..., NSER - 1 does not equal 1, 2 or 3.

## 7 Accuracy

The computations are believed to be stable.

#### 8 Further Comments

The time taken by the routine is approximately proportional to NNV  $\times$  NPARA.

# 9 Example

The example uses the data described in G13BEF in which 40 observations of an output time series and a single input series were processed. In this example a model which included seasonal differencing of order 1 was used. The 10 values of the state set and the 5 final values of PARA then obtained are used as input to this program, together with the values of 4 new observations and the transfer function orders of the input series. The model used is  $\phi_1 = 0.5158$ ,  $\Theta_1 = 0.9994$ ,  $\omega_0 = 8.6343$ ,  $\delta_1 = 0.6726$ , c = -0.3172.

The following are computed and printed out: the updated state set, the residuals  $a_t$  and the values of the components  $z_t$  and the output noise component  $n_t$  corresponding to the new observations.

#### 9.1 Program Text

```
G13BGF Example Program Text
   Mark 14 Revised. NAG Copyright 1989.
   .. Parameters ..
   INTEGER
                    NSERMX, NPMAX, NSTTFM, NNVMAX, IXXYN, IWA
                    (NSERMX=2, NPMAX=10, NSTTFM=20, NNVMAX=40,
  PARAMETER
                    IXXYN=NNVMAX,IWA=160)
   INTEGER
                    NIN, NOUT
   PARAMETER
                    (NIN=5, NOUT=6)
   .. Local Scalars ..
   INTEGER
                    I, IFAIL, J, KZEF, NNV, NPARA, NSER, NSTTF
   .. Local Arrays ..
                    PARA(NPMAX), RES(NNVMAX), STTF(NSTTFM), WA(IWA),
  real
                    XXYN(IXXYN, NSERMX)
   INTEGER
                    MR(7), MT(4,NSERMX)
   .. External Subroutines ..
  EXTERNAL
                    G13BGF
   .. Executable Statements ..
   WRITE (NOUT,*) 'G13BGF Example Program Results'
   Skip heading in data file
   READ (NIN, *)
  READ (NIN,*) NSTTF, NSER, NNV, KZEF
   IF (NSTTF.GT.O .AND. NSTTF.LE.NSTTFM .AND. NSER.GT.O .AND.
      NSER.LE.NSERMX .AND. NNV.GT.O .AND. NNV.LE.NNVMAX) THEN
      READ (NIN, \star) (MR(I), I=1,7)
      DO 20 I = 1, 4
         READ (NIN,*) (MT(I,J),J=1,NSER)
20
      CONTINUE
```

G13BGF.4 [NP3546/20A]

```
NPARA = 0
         DO 40 I = 1, NSER
            NPARA = NPARA + MT(2,I) + MT(3,I)
   40
         CONTINUE
         NPARA = NPARA + MR(1) + MR(3) + MR(4) + MR(6) + NSER
         READ (NIN,*) (STTF(I), I=1, NSTTF)
         IF (NPARA.LE.NPMAX) THEN
            READ (NIN,*) (PARA(I),I=1,NPARA) DO 60 I = 1, NNV
               READ (NIN,*) (XXYN(I,J),J=1,NSER)
   60
            CONTINUE
            IFAIL = 0
            CALL G13BGF(STTF, NSTTF, MR, NSER, MT, PARA, NPARA, NNV, XXYN, IXXYN,
                         KZEF,RES,WA,IWA,IFAIL)
            WRITE (NOUT, *)
            WRITE (NOUT,*) 'The updated state set'
            WRITE (NOUT, 99999) (STTF(I), I=1, NSTTF)
            WRITE (NOUT, *)
            WRITE (NOUT, \star) 'The residuals (after differencing)'
            DO 80 I = 1, NNV
               WRITE (NOUT, 99998) I, RES(I)
   80
            CONTINUE
            WRITE (NOUT, *)
            WRITE (NOUT, *) 'The values of z(t) and n(t)'
            DO 100 I = 1, NNV
               WRITE (NOUT, 99998) I, (XXYN(I,J), J=1, NSER)
  100
            CONTINUE
         END IF
      END IF
      STOP
99999 FORMAT (1X,6F10.4)
99998 FORMAT (1X, I4, 2F10.4)
      END
```

# 9.2 Program Data

```
G13BGF Example Program Data
   10
                  1
         2
              4
    1
         0
              0
                  0
                       1
                            1
    1
         0
    0
        0
    3
        Ω
  6.0530 184.4749 -80.0885 -75.1704 -76.9481 -81.4749 0.7776 -2.6190
 -2.3054 -1.1963
         0.9994
                   8.6343 0.6726 -0.3172
  0.5158
  5.9410 96.0000
  5.3860 95.0000
5.8110 80.0000
  6.7160 88.0000
```

[NP3546/20A] G13BGF.5

# 9.3 Program Results

```
G13BGF Example Program Results

The updated state set
    6.7160   158.3155   -80.3412   -74.9035   -80.7814   -70.3155
    0.8416   -2.0333   -5.8201   10.2810

The residuals (after differencing)
    1    1.4586
    2   -2.4674
    3   -4.7714
    4   13.2830

The values of z(t) and n(t)
    1   176.3412   -80.3412
    2   169.9035   -74.9035
    3   160.7814   -80.7814
    4   158.3155   -70.3155
```

G13BGF.6 (last) [NP3546/20A]