

NAG Fortran Library Routine Document

X04DAF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

X04DAF is an easy-to-use routine to print a *complex* matrix stored in a two-dimensional array.

2 Specification

```
SUBROUTINE X04DAF(MATRIX, DIAG, M, N, A, LDA, TITLE, IFAIL)
INTEGER          M, N, LDA, IFAIL
complex        A(LDA,*)
CHARACTER*1      MATRIX, DIAG
CHARACTER*(*)    TITLE
```

3 Description

X04DAF prints a *complex* matrix. It is an easy-to-use driver for X04DBF. The routine uses default values for the format in which numbers are printed, for labelling the rows and columns, and for output record length.

X04DAF will choose a format code such that numbers will be printed with an F8.4, an F11.4 or a 1PE13.4 format. The F8.4 code is chosen if the sizes of all the matrix elements to be printed lie between 0.001 and 1.0. The F11.4 code is chosen if the sizes of all the matrix elements to be printed lie between 0.001 and 9999.9999. Otherwise the 1PE13.4 code is chosen. The chosen code is used to print each complex element of the matrix with the real part above the imaginary part.

The matrix is printed with integer row and column labels, and with a maximum record length of 80.

The matrix is output to the unit defined by X04ABF.

4 References

None.

5 Parameters

1: MATRIX – CHARACTER*1 *Input*

On entry: indicates the part of the matrix to be printed, as follows:

if MATRIX = 'G' (General), the whole of the rectangular matrix;

if MATRIX = 'L' (Lower), the lower triangle of the matrix, or the lower trapezium if the matrix has more rows than columns;

if MATRIX = 'U' (Upper), the upper triangle of the matrix, or the upper trapezium if the matrix has more columns than rows.

Constraint: MATRIX must be one of 'G', 'L' or 'U'.

2: DIAG – CHARACTER*1 *Input*

On entry: unless MATRIX = 'G', DIAG must specify whether the diagonal elements of the matrix are to be printed, as follows:

if DIAG = 'B' (Blank), the diagonal elements of the matrix are not referenced and not printed;

if `DIAG = 'U'` (Unit diagonal), the diagonal elements of the matrix are not referenced, but are assumed all to be unity, and are printed as such;

if `DIAG = 'N'` (Non-unit diagonal), the diagonal elements of the matrix are referenced and printed.

If `MATRIX = 'G'`, then `DIAG` need not be set.

Constraint: If `MATRIX` \neq 'G', then `DIAG` must be one of 'B', 'U' or 'N'.

3: M – INTEGER *Input*
 4: N – INTEGER *Input*

On entry: the number of rows and columns of the matrix, respectively, to be printed.

If either M or N is less than 1, X04DAF will exit immediately after printing TITLE; no row or column labels are printed.

5: A(LDA,*) – **complex** array *Input*

Note: the second dimension of the array A must be at least $\max(1, N)$.

On entry: the matrix to be printed. Only the elements that will be referred to, as specified by parameters `MATRIX` and `DIAG`, need be set.

6: LDA – INTEGER *Input*

On entry: the first dimension of the array A as declared in the (sub)program from which X04DAF is called.

Constraint: $LDA \geq M$.

7: TITLE – CHARACTER*(*) *Input*

On entry: a title to be printed above the matrix. If `TITLE = ' '`, no title (and no blank line) will be printed.

If `TITLE` contains more than 80 characters, the contents of `TITLE` will be wrapped onto more than one line, with the break after 80 characters.

Any trailing blank characters in `TITLE` are ignored.

8: IFAIL – INTEGER *Input/Output*

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**

6 Error Indicators and Warnings

If on entry `IFAIL = 0` or `-1`, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, `MATRIX` \neq 'G', 'L' or 'U'.

IFAIL = 2

On entry, MATRIX = 'L' or 'U', but DIAG \neq 'N', 'U' or 'B'.

IFAIL = 3

On entry, LDA < M.

7 Accuracy

Not applicable.

8 Further Comments

A call to X04DAF is equivalent to a call to X04DBF with the following argument values:

```

NCOLS = 80
INDENT = 0
LABROW = 'I'
LABCOL = 'I'
FORMAT = ' '
USEFRM = 'A'

```

9 Example

This example program calls X04DAF twice, first to print a 4 by 3 rectangular matrix, and then to print a 4 by 4 lower triangular matrix.

9.1 Program Text

Note: the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```

*      X04DAF Example Program Text
*      Mark 14 Release.  NAG Copyright 1989.
*      .. Parameters ..
      INTEGER          NOUT
      PARAMETER       (NOUT=6)
      INTEGER          NMAX, LDA
      PARAMETER       (NMAX=4,LDA=NMAX)
*      .. Local Scalars ..
      real            AA
      INTEGER          I, IFAIL, J
*      .. Local Arrays ..
      complex        A(LDA,NMAX)
*      .. External Subroutines ..
      EXTERNAL        X04DAF
*      .. Intrinsic Functions ..
      INTRINSIC       cmplx
*      .. Executable Statements ..
      WRITE (NOUT,*) 'X04DAF Example Program Results'
      WRITE (NOUT,*)
*      Generate an array of data
      DO 40 J = 1, NMAX
         DO 20 I = 1, LDA
            AA = 10*I + J
            A(I,J) = cmplx(AA,-AA)
20      CONTINUE
40     CONTINUE
*
*      IFAIL = 0
*
*      Print 4 by 3 rectangular matrix
      CALL X04DAF('General',' ',4,3,A,LDA,'Example 1:',IFAIL)
*
      WRITE (NOUT,*)

```

```
*  
*   Print 4 by 4 lower triangular matrix  
*   CALL X04DAF('Lower','Non-unit',4,4,A,LDA,'Example 2:',IFAIL)  
*  
*   STOP  
*   END
```

9.2 Program Data

None.

9.3 Program Results

X04DAF Example Program Results

Example 1:

	1	2	3
1	11.0000 -11.0000	12.0000 -12.0000	13.0000 -13.0000
2	21.0000 -21.0000	22.0000 -22.0000	23.0000 -23.0000
3	31.0000 -31.0000	32.0000 -32.0000	33.0000 -33.0000
4	41.0000 -41.0000	42.0000 -42.0000	43.0000 -43.0000

Example 2:

	1	2	3	4
1	11.0000 -11.0000			
2	21.0000 -21.0000	22.0000 -22.0000		
3	31.0000 -31.0000	32.0000 -32.0000	33.0000 -33.0000	
4	41.0000 -41.0000	42.0000 -42.0000	43.0000 -43.0000	44.0000 -44.0000
