# NAG Fortran Library Routine Document X04CDF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

# 1 Purpose

X04CDF prints a *real* triangular matrix stored in a packed one-dimensional array.

# 2 Specification

```
SUBROUTINE X04CDF(UPLO, DIAG, N, A, FORMAT, TITLE, LABROW, RLABS,

LABCOL, CLABS, NCOLS, INDENT, IFAIL)

INTEGER

N, NCOLS, INDENT, IFAIL

real

CHARACTER*1

UPLO, DIAG, LABROW, LABCOL

CHARACTER*(*)

FORMAT, TITLE, RLABS(*), CLABS(*)
```

# 3 Description

X04CDF prints a *real* triangular matrix stored in packed form, using a format specifier supplied by the user. The matrix must be packed by column. The matrix is output to the unit defined by X04ABF.

## 4 References

None.

## 5 Parameters

## 1: UPLO - CHARACTER\*1

Input

On entry: indicates the type of the matrix to be printed, as follows:

if UPLO = 'L' (Lower), the matrix is lower triangular. In this case, the packed array A holds the matrix elements in the following order:  $(1,1),(2,1),\ldots,(N,1),(2,2),(3,2),\ldots,(N,2),$  etc.;

if UPLO = 'U' (Upper), the matrix is upper triangular. In this case, the packed array A holds the matrix elements in the following order: (1,1), (1,2), (2,2), (1,3), (2,3), (3,3), (1,4), etc.

Constraint: UPLO must be 'L' or 'U'.

## 2: DIAG - CHARACTER\*1

Input

On entry: indicates whether the diagonal elements of the matrix are to be printed, as follows:

if DIAG = 'B' (Blank), the diagonal elements of the matrix are not referenced and not printed;

if DIAG = 'U' (Unit diagonal), the diagonal elements of the matrix are not referenced, but are assumed all to be unity, and are printed as such;

if DIAG = 'N' (Non-unit diagonal), the diagonal elements of the matrix are referenced and printed.

Constraint: DIAG must be one of 'B', 'U' or 'N'.

[NP3546/20A] X04CDF.1

3: N – INTEGER Input

On entry: the order of the matrix to be printed.

If N is less than 1, X04CDF will exit immediately after printing TITLE; no row or column labels are printed.

4: A(\*) - real array Input

**Note:** the dimension of the array A must be at least max(1, N\*(N+1)/2).

On entry: the matrix to be printed. Note that A must have space for the diagonal elements of the matrix, even if these are not stored.

#### 5: FORMAT – CHARACTER\*(\*)

Input

On entry: a valid Fortran format code. This may be any format code allowed on the system, whether it is standard Fortran or not. FORMAT is used to print elements of the matrix A. It may or may not be enclosed in brackets. Examples of valid values for FORMAT are 'F11.4', '1PE13.5', 'G14.5'.

In addition, there are two special codes which force X04CDF to choose its own format code:

FORMAT = ' ' means that X04CDF will choose a format code such that numbers will be printed with an F8.4, an F11.4 or a 1PE13.4 format. The F8.4 code is chosen if the sizes of all the matrix elements to be printed lie between 0.001 and 1.0. The F11.4 code is chosen if the sizes of all the matrix elements to be printed lie between 0.001 and 9999.9999. Otherwise the 1PE13.4 code is chosen.

FORMAT = '\*' means that X04CDF will choose a format code such that numbers will be printed to as many significant digits as are necessary to distinguish between neighbouring machine numbers. Thus any two numbers that are stored with different internal representations should look different on output. Whether they do in fact look different will depend on the run-time library of the Fortran compiler in use.

Constraint: the character length of FORMAT must be < 80.

## 6: TITLE – CHARACTER\*(\*)

Input

On entry: a title to be printed above the matrix. If TITLE = ' ', no title (and no blank line) will be printed.

If TITLE contains more than NCOLS characters, the contents of TITLE will be wrapped onto more than one line, with the break after NCOLS characters.

Any trailing blank characters in TITLE are ignored.

## 7: LABROW – CHARACTER\*1

Input

On entry: indicates the type of labelling to be applied to the rows of the matrix, as follows:

if LABROW = 'N', X04CDF prints no row labels;

if LABROW = 'I', X04CDF prints integer row labels;

if LABROW = 'C', X04CDF prints character labels, which must be supplied in array RLABS.

Constraint: LABROW = 'N', 'I' or 'C'.

### 8: RLABS(\*) - CHARACTER\*(\*) array

Innu

On entry: if LABROW = 'C', RLABS must be dimensioned at least of length N and must contain labels for the rows of the matrix, otherwise RLABS may be dimensioned of length 1.

Labels are right justified when output, in a field which is as wide as necessary to hold the longest row label. Note that this field width is subtracted from the number of usable columns, NCOLS.

X04CDF.2 [NP3546/20A]

#### 9: LABCOL - CHARACTER\*1

Input

On entry: indicates the type of labelling to be applied to the columns of the matrix, as follows:

If LABCOL = 'N', X04CDF prints no column labels.

If LABCOL = 'I', X04CDF prints integer column labels.

If LABCOL = 'C', X04CDF prints character labels, which must be supplied in array CLABS.

Constraint: LABCOL = 'N', 'I' or 'C'.

#### 10: CLABS(\*) - CHARACTER\*(\*) array

Input

On entry: if LABCOL = 'C', CLABS must be dimensioned at least of length N and must contain labels for the columns of the matrix, otherwise CLABS may be dimensioned of length 1.

Labels are right-justified when output. Any label that is too long for the column width, which is determined by FORMAT, is truncated.

11: NCOLS - INTEGER

Input

On entry: the maximum output record length. If the number of columns of the matrix is too large to be accommodated in NCOLS characters, the matrix will be printed in parts, containing the largest possible number of matrix columns, and each part separated by a blank line.

NCOLS must be large enough to hold at least one column of the matrix using the format specifier in FORMAT. If a value less than 0 or greater than 132 is supplied for NCOLS, then the value 80 is used instead.

#### 12: INDENT – INTEGER

Input

*On entry*: the number of columns by which the matrix (and any title and labels) should be indented. The effective value of NCOLS is reduced by INDENT columns. If a value less than 0 or greater than NCOLS is supplied for INDENT, the value 0 is used instead.

#### 13: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

# 6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, UPLO  $\neq$  'L' or 'U'.

IFAIL = 2

On entry, DIAG  $\neq$  'N', 'U' or 'B'.

IFAIL = 3

On entry, variable FORMAT is more than 80 characters long.

[NP3546/20A] X04CDF.3

#### IFAIL = 4

The code supplied in FORMAT cannot be used to output a number. FORMAT probably has too wide a field width or contains an illegal edit descriptor.

#### IFAIL = 5

On entry, either LABROW or LABCOL  $\neq$  'N', 'I' or 'C'.

```
IFAIL = 6
```

The quantity NCOLS - INDENT - LABWID (where LABWID is the width needed for the row labels) is not large enough to hold at least one column of the matrix.

# 7 Accuracy

Not applicable.

## **8** Further Comments

None.

# 9 Example

The example program calls X04CDF twice, first to print a 4 by 4 lower triangular matrix, and then to print a 5 by 5 upper triangular matrix; various options for labelling and formatting are illustrated.

## 9.1 Program Text

**Note:** the listing of the example program presented below uses **bold italicised** terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
X04CDF Example Program Text
   Mark 14 Release. NAG Copyright 1989.
   .. Parameters ..
                     NOUT
   INTEGER
   PARAMETER
                     (NOUT=6)
   INTEGER
                   NMAX, LA
                    (NMAX=5,LA=(NMAX*(NMAX+1))/2)
   PARAMETER
   .. Local Scalars ..
   INTEGER
                     I, IFAIL, INDENT, NCOLS
   .. Local Arrays ..
   real
                     A(LA)
   CHARACTER*7
                    CLABS(NMAX), RLABS(NMAX)
   .. External Subroutines ..
   EXTERNAL
                    X04CDF
   .. Data statements ..
                    CLABS/'Un', 'Deux', 'Trois', 'Quatre', 'Cinq'/
RLABS/'Uno', 'Duo', 'Tre', 'Quattro', 'Cinque'/
   DATA
   .. Executable Statements ..
   WRITE (NOUT,*) 'X04CDF Example Program Results'
   WRITE (NOUT, *)
   Generate an array of data
   DO 20 I = 1, LA
     A(I) = I
20 CONTINUE
   NCOLS = 80
   INDENT = 0
   IFAIL = 0
   Print order 4 lower triangular matrix with default format and
   integer row and column labels
   CALL X04CDF('Lower','Non-unit',4,A,' ','Example 1:','Integer',
```

X04CDF.4 [NP3546/20A]

## 9.2 Program Data

None.

# 9.3 Program Results

X04CDF Example Program Results

```
Example 1:
            1
                                  3
                                              4
       1.0000
       2.0000
2
                 5.0000
       3.0000
                  6.0000
                             8.0000
                                       10.0000
       4.0000
                  7.0000
                             9.0000
Example 2:
              Un
                    Deux
                           Trois Quatre
                                            Cinq
                            4.00
                                            11.00
    Uno
            1.00
                    2.00
                                    7.00
                    1.00
                            5.00
                                    8.00
                                            12.00
   Duo
   Tre
                            1.00
                                    9.00
                                            13.00
Quattro
                                     1.00
                                            14.00
 Cinque
                                             1.00
```

[NP3546/20A] X04CDF.5 (last)