

Oracle® Fleet Patching and Provisioning Administrator's Guide



21c
F30287-01
November 2020

The Oracle logo, consisting of a solid red square with the word "ORACLE" in white, uppercase, sans-serif font centered within it.

ORACLE®

Oracle Fleet Patching and Provisioning Administrator's Guide, 21c

F30287-01

Copyright © 2016, 2020, Oracle and/or its affiliates.

Primary Authors: Subhash Chandra, Eric Belden

Contributors: Jonathan Creighton, Kamalesh Ramasamy, Kannan S. Viswanathan, Rahul Desale, Ricardo A. Gonzalez, Ricardo Tamez Durandean, Sampath Ravindhran, Siddharth Shankaran, Soo Huey Wong

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

1 Oracle Fleet Patching and Provisioning

About Oracle Fleet Patching and Provisioning	1-1
Oracle Fleet Patching and Provisioning Architecture	1-8
Oracle Fleet Patching and Provisioning Server	1-10
Oracle Fleet Patching and Provisioning Targets	1-11
Oracle Fleet Patching and Provisioning Clients	1-11
Authentication Options for Oracle Fleet Patching and Provisioning Operations	1-12
Oracle Fleet Patching and Provisioning Roles	1-13
Oracle Fleet Patching and Provisioning Images	1-16
Gold Image Distribution Among Oracle Fleet Patching and Provisioning Servers	1-16
Oracle Fleet Patching and Provisioning Server Auditing	1-19
Oracle Fleet Patching and Provisioning Notifications	1-19
Oracle Fleet Patching and Provisioning Implementation	1-19
Creating a Fleet Patching and Provisioning Server	1-19
Adding Gold Images to the Fleet Patching and Provisioning Server	1-20
Image State	1-21
Image Series	1-21
Image Type	1-22
Provisioning Copies of Gold Images	1-23
User Group Management in Fleet Patching and Provisioning	1-23
Storage Options for Provisioned Software	1-26
Provisioning for a Different User	1-27
Propagating Images Between Fleet Patching and Provisioning Servers	1-27

2 Managing Oracle Grid Infrastructure and Database Software

Patching Oracle Grid Infrastructure and Oracle Database Using Batches	2-1
Oracle Grid Infrastructure Management	2-5
About Deploying Oracle Grid Infrastructure Using Oracle Fleet Patching and Provisioning	2-5
Provisioning Oracle Grid Infrastructure Software	2-6
Patching Oracle Grid Infrastructure Software	2-8
Patching Oracle Grid Infrastructure Using the Rolling Method	2-8

Patching Oracle Grid Infrastructure Using the Non-Rolling Method	2-9
Combined Oracle Grid Infrastructure and Oracle Database Patching	2-10
Zero-Downtime Oracle Grid Infrastructure Patching	2-12
Patching Oracle Grid Infrastructure Using Local-Mode Configuration	2-13
Error Prevention and Automated Recovery Options	2-14
Upgrading Oracle Grid Infrastructure Software	2-15
Oracle Fleet Patching and Provisioning Self Upgrade	2-16
Starting Oracle FPP Server After Manually Upgrading Oracle Grid Infrastructure	2-17
Oracle Fleet Patching and Provisioning Automation for GIMR Integration	2-17
Oracle Database Software Management	2-18
Provisioning a Copy of a Gold Image of a Database Home	2-19
Creating an Oracle Database on a Copy of a Gold Image	2-19
Patching Oracle Database Software	2-20
Patching Oracle Database with the Independent Automaton	2-22
Upgrading Oracle Database Software	2-23
Combined Oracle Exadata Database Node and Grid Infrastructure Patching	2-24
Zero-Downtime Upgrade	2-27
Running a Zero-Downtime Upgrade Using Oracle GoldenGate for Replication	2-29
Running a Zero-Downtime Upgrade Using Oracle Data Guard for Replication	2-31
Customizing Zero-Downtime Upgrades	2-32
Persistent Home Path During Patching	2-33
User-Defined Actions	2-34
Job Scheduler for Operations	2-40
Oracle Restart Patching and Upgrading	2-42

3 Managing Oracle Fleet Patching and Provisioning Clients

Creating a Fleet Patching and Provisioning Client	3-1
Enabling and Disabling Fleet Patching and Provisioning Clients	3-3
Deleting a Fleet Patching and Provisioning Client	3-4
Creating Users and Assigning Roles for Fleet Patching and Provisioning Client	
Cluster Users	3-5
Managing the Fleet Patching and Provisioning Client Password	3-5

4 Oracle Fleet Patching and Provisioning Use Cases

Creating an Oracle Grid Infrastructure 12c Release 2 Deployment	4-1
Provisioning an Oracle Database Home and Creating a Database	4-2
Provisioning a Pluggable Database	4-3
Upgrading to Oracle Grid Infrastructure 12c Release 2	4-3
Patching Oracle Grid Infrastructure Without Changing the Grid Home Path	4-4
Patching Oracle Grid Infrastructure and Oracle Databases Simultaneously	4-5

Patching Oracle Database 12c Release 1 Without Downtime	4-6
Upgrading to Oracle Database 12c Release 2	4-7
Adding a Node to a Cluster and Scaling an Oracle RAC Database to the Node	4-8
Adding Gold Images for Fleet Patching and Provisioning	4-9
User Actions for Common Fleet Patching and Provisioning Tasks	4-10

A Oracle Fleet Patching and Provisioning Control (RHPCTL) Command Reference

RHPCTL Overview	A-1
Using RHPCTL Help	A-2
RHPCTL Command Reference	A-2
rhpctl delete audit	A-2
rhpctl modify audit	A-2
rhpctl query audit	A-3
rhpctl add client	A-4
rhpctl allow client	A-5
rhpctl delete client	A-6
rhpctl disallow client	A-7
rhpctl discover client	A-8
rhpctl export client	A-9
rhpctl modify client	A-9
rhpctl query client	A-10
rhpctl update client	A-12
rhpctl verify client	A-12
rhpctl add credentials	A-13
rhpctl delete credentials	A-14
rhpctl add database	A-14
rhpctl addnode database	A-17
rhpctl addpdb database	A-18
rhpctl deletepdb database	A-20
rhpctl delete database	A-21
rhpctl deletenode database	A-22
rhpctl move database	A-24
rhpctl movepdb database	A-28
rhpctl upgrade database	A-29
rhpctl zdtupgrade database	A-31
rhpctl update exadata	A-34
rhpctl addnode gihome	A-35
rhpctl deletenode gihome	A-37
rhpctl move gihome	A-38

rhctl upgrade gihome	A-42
rhctl add image	A-44
rhctl allow image	A-45
rhctl delete image	A-45
rhctl deploy image	A-46
rhctl disallow image	A-46
rhctl import image	A-47
rhctl instantiate image	A-49
rhctl modify image	A-50
rhctl query image	A-50
rhctl promote image	A-52
rhctl unstantiate image	A-52
rhctl add imagetype	A-53
rhctl allow imagetype	A-54
rhctl delete imagetype	A-54
rhctl disallow imagetype	A-54
rhctl modify imagetype	A-55
rhctl query imagetype	A-55
rhctl delete job	A-57
rhctl query job	A-57
rhctl collect osconfig	A-59
rhctl compare osconfig	A-59
rhctl disable osconfig	A-60
rhctl enable osconfig	A-60
rhctl query osconfig	A-61
rhctl query peerserver	A-62
rhctl add role	A-62
rhctl delete role	A-64
rhctl grant role	A-64
rhctl query role	A-65
rhctl revoke role	A-66
rhctl add series	A-66
rhctl delete series	A-67
rhctl deleteimage series	A-67
rhctl insertimage series	A-68
rhctl query series	A-69
rhctl subscribe series	A-70
rhctl unsubscribe series	A-71
rhctl export server	A-71
rhctl query server	A-71
rhctl register server	A-72

rhctl unregister server	A-72
rhctl delete user	A-73
rhctl modify user	A-73
rhctl register user	A-74
rhctl unregister user	A-74
rhctl add useraction	A-75
rhctl delete useraction	A-76
rhctl modify useraction	A-77
rhctl query useraction	A-78
rhctl add workingcopy	A-79
rhctl addnode workingcopy	A-85
rhctl delete workingcopy	A-86
rhctl query workingcopy	A-88
rhctl update workingcopy	A-89

Glossary

Index

Preface

Information in *Oracle Fleet Patching and Provisioning Administrator's Guide* applies to Oracle Fleet Patching and Provisioning as it runs on all platforms unless otherwise noted. Where necessary, this manual refers to platform-specific documentation.

This Preface contains these topics:

- [Audience](#)
- [Documentation Accessibility](#)
- [Related Documents](#)
- [Conventions](#)

Audience

The *Oracle Fleet Patching and Provisioning Administrator's Guide* is intended for database administrators and system administrators who provision and maintain Oracle homes.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Related Documents

For more information, see the Oracle resources listed in this section.

- Platform-specific Oracle Clusterware and Oracle RAC installation guides
Each platform-specific Oracle Database 11g installation media contains a copy of an Oracle Clusterware and Oracle RAC platform-specific installation and configuration guide in HTML and PDF formats. These installation books contain the preinstallation, installation, and postinstallation information for the various UNIX, Linux, and Windows platforms on which Oracle Clusterware and Oracle RAC operate.
- *Oracle Clusterware Administration and Deployment Guide*
- *Oracle Real Application Clusters Administration and Deployment Guide*
- *Oracle Database Administrator's Guide*

- *Oracle Database Net Services Administrator's Guide*
- *Oracle Database Error Messages Reference*

 **See Also:**

- *Oracle Database Licensing Information User Manual* to determine whether a feature is available on your edition of Oracle Database
- *Oracle Database New Features Guide* for a complete description of the new features in this release
- *Oracle Database Upgrade Guide* for a complete description of the deprecated and desupported features in this release

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

1

Oracle Fleet Patching and Provisioning

Oracle Fleet Patching and Provisioning is a software lifecycle management method for provisioning and maintaining Oracle homes.

Oracle Fleet Patching and Provisioning (Oracle FPP) enables mass deployment and maintenance of standard operating environments for databases, clusters, and user-defined software types. With Oracle Fleet Patching and Provisioning, you can also install clusters and provision, patch, scale, and upgrade Oracle Grid Infrastructure and Oracle Database 11g release 2 (11.2), and later. Additionally, you can provision applications and middleware.

Note:

Starting with Oracle Grid Infrastructure 19c, the feature formerly known as Rapid Home Provisioning (RHP) is now Oracle Fleet Patching and Provisioning (Oracle FPP).

This chapter includes the following topics:

- [About Oracle Fleet Patching and Provisioning](#)
- [Oracle Fleet Patching and Provisioning Architecture](#)
- [Oracle Fleet Patching and Provisioning Implementation](#)

Related Topics

- *Oracle Real Application Clusters Installation Guide for Linux and UNIX*

About Oracle Fleet Patching and Provisioning

Oracle Fleet Patching and Provisioning (FPP) is a service in Oracle Grid Infrastructure.

You can use Oracle Fleet Patching and Provisioning in either of the following modes:

- As a central server ([Fleet Patching and Provisioning Server](#)), that stores and manages standardized [images](#), called [gold images](#). You can deploy gold images to any number of nodes across a data center. You can use the deployed homes to create new clusters and databases, and patch, upgrade, and scale existing installations.

The server manages software homes on the cluster hosting the Oracle Fleet Patching and Provisioning Server, itself, Oracle Fleet Patching and Provisioning Clients, and can also manage installations running Oracle Grid Infrastructure 11g release 2 (11.2.0.3 and 11.2.0.4), 12c release 1 (12.1.0.2), and later releases. The server can also manage installations running no grid infrastructure.

An Oracle Fleet Patching and Provisioning Server can provision new installations and can manage existing installations without any changes to the existing installations (such as no agent, daemon, or configuration prerequisites). Oracle

Fleet Patching and Provisioning Servers also include capabilities for automatically sharing gold images among peer Oracle Fleet Patching and Provisioning Servers to support enterprises with geographically distributed data centers.

- As a client (Oracle Fleet Patching and Provisioning Client), that can be managed from the central Oracle Fleet Patching and Provisioning Server or directly by running commands on the Oracle Fleet Patching and Provisioning Client, itself. As with the Oracle Fleet Patching and Provisioning Server, the Oracle Fleet Patching and Provisioning Client is a service built in to Oracle Grid Infrastructure and is available with Oracle Grid Infrastructure 12c release 2 (12.2.0.1), and later. The Oracle Fleet Patching and Provisioning Client service can retrieve gold images from the Oracle Fleet Patching and Provisioning Server, upload new images based on policy, and apply maintenance operations to itself.

For patching operations, a third option is available with Oracle Database and Oracle Grid Infrastructure 18c, and later. The procedures for updating database and grid infrastructure homes have been modularized into independent *automatons* that are included with Oracle Database and Oracle Grid Infrastructure, and can be run locally without any central Oracle Fleet Patching and Provisioning Server in the architecture. This provides an immediate entry point to the capabilities of Oracle Fleet Patching and Provisioning as soon as you bring up an Oracle Database or cluster.



Note:

Combined Oracle FPP patching for Oracle Grid Infrastructure and Oracle Database is not supported for standalone configurations.

This topic includes information about the following:

- [Oracle Fleet Patching and Provisioning Advantages](#)
- [Managing Oracle software using Oracle Fleet Patching and Provisioning](#)
- [Oracle Fleet Patching and Provisioning Automatons](#)
- [Global Fleet Standardization and Management](#)
- [Flexibility and Extensibility](#)
- [Other Oracle Fleet Patching and Provisioning Features](#)

Oracle Fleet Patching and Provisioning Advantages

Deploying Oracle software using Oracle Fleet Patching and Provisioning has the following advantages:

- Ensures standardization and enables high degrees of automation with gold images and managed lineage of deployed software.
- Minimizes downtime by deploying new homes as images (called gold images) out-of-place, without disrupting active databases or clusters.
- Simplifies maintenance by providing automatons which are invoked with a simple, consistent API across database versions and deployment models.
- Reduces maintenance risk with built-in validations and a *dry run* mode to test the operations.

- Enables you to resume or restart the commands in the event of an unforeseen issue, reducing the risk of maintenance operations.
- Minimizes and often eliminates the impact of patching and upgrades, with features that include:
 - Zero-downtime database upgrade with fully automated upgrade, executed entirely within the deployment without requiring any extra nodes or external storage.
 - Adaptive management of database sessions and OJVM during rolling patching.
 - Options for management of consolidated deployments.
- The deployment and maintenance operations enable customizations to include environment-specific actions into the automated workflow.

Managing Oracle software using Oracle Fleet Patching and Provisioning

When you manage Oracle software using Oracle Fleet Patching and Provisioning, Oracle FPP:

- Ensures standardization and enables high degrees of automation with gold images and managed lineage of deployed software.
- Minimizes the maintenance window by deploying new homes (gold images) out-of-place, without disrupting active databases or clusters.
- Simplifies maintenance by providing automatons that are invoked with an API across database versions and deployment models.
- Reduces maintenance risk with built-in validations and a dry-run mode to ensure operations will succeed end-to-end.
- In the event of an issue, commands are resumable and restartable, further reducing risk of maintenance operations.
- Minimizes and, in many cases, eliminates the impact of patching and upgrades, with features that include:
 - Zero-downtime database upgrade: A fully-automated upgrade executed entirely within the deployment with no extra nodes or external storage required.
 - Adaptive management of database sessions and OJVM during rolling patching.
 - Options for fine-grained management of consolidated deployments.

The deployment and maintenance operations are extensible, allowing customizations to include environment-specific actions into the automated workflow.

Oracle Fleet Patching and Provisioning Automatons

- *Zero-downtime database upgrade* automates all of the steps involved in a database upgrade to minimize or even eliminate application downtime while upgrading an Oracle database. It also minimizes resource requirements and provides a fallback path in case the upgrade must be rolled back.
- *Adaptive Oracle RAC Rolling Patching for OJVM Deployments*: In a clustered environment, the default approach for Oracle Fleet Patching and Provisioning for patching a database is Oracle RAC rolling patching. However non-rolling may be required if the patched database home contains OJVM patches. In this case,

Oracle Fleet Patching and Provisioning determines whether rolling patching is possible and does so, if applicable.

- *Dry-run command evaluation*: Before running any command, Oracle Fleet Patching and Provisioning checks various preconditions to ensure the command will succeed. However, some conditions cannot be detected prior to a command running. And, while Oracle Fleet Patching and Provisioning allows a failed command to be reverted or resumed after an error condition is corrected, it is preferable to address as many potential issues as possible before the command is run. The command evaluation mode will test the preconditions for a given command, without making any changes, and report potential problems and correct them before the command is actually run.
- *Independent automatons*: Prior to Oracle Database 18c, performing any Oracle Fleet Patching and Provisioning operation (for example, switching a database home to a later version) required the presence of a central Oracle Fleet Patching and Provisioning Server. Beginning with Oracle Database 18c, key functionality can be performed independently, with no central Oracle Fleet Patching and Provisioning Server in the architecture.

 **Note:**

When you install Oracle Grid Infrastructure, the Oracle Fleet Patching and Provisioning Server is configured, by default, in the *local* mode to support the *local switch home* capability. If you must configure the general Oracle Fleet Patching and Provisioning Server product, then you must remove the current local-mode Oracle Fleet Patching and Provisioning Server, using the following commands, as *root*:

```
# srvctl stop rhpserver
```

Ignore a message similar to "Fleet Patching and Provisioning Server is not running".

```
# srvctl remove rhpserver
```

Refer to *Oracle Clusterware Administration and Deployment Guide* for information about `srvctl remove rhpserver` and `srvctl stop rhpserver`.

Global Fleet Standardization and Management

- *Sharing gold images between peer Oracle Fleet Patching and Provisioning Servers*: Large enterprises typically host multiple data centers and, within each data center, there may be separate network segments. In the Oracle Fleet Patching and Provisioning architecture, one Oracle Fleet Patching and Provisioning Server operates on a set of targets within a given data center (or network segment of a data center). Therefore each data center requires at least one Oracle Fleet Patching and Provisioning Server.

While each data center may have some unique requirements in terms of the gold images that target servers will use, the goal of standardization is using the same gold image across all data centers whenever possible. To that end, Oracle Fleet Patching and Provisioning supports peer-to-peer sharing of gold images to easily

propagate gold images among multiple Oracle Fleet Patching and Provisioning Servers.

- *Gold image drift detection and aggregation:* After you provision a software home from a gold image, you may have to apply a patch directly to the deployed home. At this point the deployed home has drifted from the gold image. Oracle Fleet Patching and Provisioning provides two capabilities for monitoring and reporting drift:
 - Oracle Fleet Patching and Provisioning compares a specific home to its parent gold image and lists any patches that are applied to the home but that are not in the gold image.
 - Oracle Fleet Patching and Provisioning compares a specific gold image to all of its descendant homes and lists the aggregation of all patches applied to those homes that are not in the gold image. This provides a build specification for a new gold image that could be applied to all of the descendants of the original gold image, such that no patches will be lost from any of those deployments.

See Also:

- [rhctl query image](#) for information about the `-drift` option for this command
- [rhctl query workingcopy](#) for information about the `-drift` option for this command

- *Configuration collection and reporting:* The Oracle Fleet Patching and Provisioning Server can collect and retain operating system configuration and the root file system contents of specified Oracle Fleet Patching and Provisioning Clients. If an Oracle Fleet Patching and Provisioning Client node is rendered unusable (for example, a user accidentally deletes or changes operating system configuration or the root file system), then it can be difficult to determine the problem and correct it. This feature automates the collection of relevant information, enabling simple restoration in the event of node failure.

Flexibility and Extensibility

- *RESTful API:* Oracle Fleet Patching and Provisioning provides a RESTful API for many common operations, including provisioning, patching, upgrading, and query operations.

See Also:

Oracle Database REST API Reference

- *Customizable authentication:* Host-to-host authentication in certain environments, particularly in compliance-conscious industries, such as financials and e-commerce, often uses technologies and products that are not supported, natively, by Oracle Fleet Patching and Provisioning. This feature allows integrating Oracle Fleet Patching and Provisioning authentication with the mechanisms in use at your data center.

- *Command scheduler:* The ability to schedule and bundle automated tasks is essential for maintenance of a large database estate. Oracle Fleet Patching and Provisioning supports scheduling tasks such as provisioning software homes, switching to a new home, and scaling a cluster. Also, you can add a list of clients to a command, facilitating large-scale operations.
- *Configurable connectivity:* As security concerns and compliance requirements increase, so do the restrictions on connectivity across the intranets of many enterprises. You can configure the small set ports used for communication between the Oracle Fleet Patching and Provisioning Server and its Clients, allowing low-impact integration into firewalled or audit-conscious environments.

Other Oracle Fleet Patching and Provisioning Features

- *Zero-downtime upgrade:* Automation of all of upgrade steps involved minimizes or even eliminates application downtime while upgrading an Oracle Database. It also minimizes resource requirements and provides a fallback path in case you must roll back the upgrade. You can run a zero-downtime upgrade on certain versions of Oracle RAC and Oracle RAC One Node databases.
- *Provision new server pools:* The Oracle Fleet Patching and Provisioning Server can install and configure Oracle Grid Infrastructure (11g release 2 (11.2.0.4), and 12c release 1 (12.1.0.2), release 2 (12.2), and later releases) on nodes that have no Oracle software inventory and can then manage those deployments with the full complement of Oracle Fleet Patching and Provisioning functionality.
- *Provision and manage any software home:* Oracle Fleet Patching and Provisioning enables you to create a gold image from any software home. You can then provision that software to any Oracle Fleet Patching and Provisioning Client or target as a working copy of a gold image. The software may be any binary that you will run on an Oracle Fleet Patching and Provisioning Client or target.
- *Provision, scale, patch, and upgrade Oracle Grid Infrastructure:* The Oracle Fleet Patching and Provisioning Server can provision Oracle Grid Infrastructure 11g release 2 (11.2.0.4) homes, and later, add or delete nodes from an Oracle Grid Infrastructure configuration, and can also be used to patch and upgrade Oracle Grid Infrastructure homes. In addition, there is a rollback capability that facilitates undoing a failed patch procedure. While patching Oracle Grid Infrastructure, you can use Oracle Fleet Patching and Provisioning to optionally patch any database homes hosted on the cluster.
- *Provision, scale, patch, and upgrade Oracle Database:* You can use Oracle Fleet Patching and Provisioning, you can provision, scale, and patch Oracle Database 11g release 2 (11.2.0.4), and later releases. You can also upgrade Oracle Databases from 11g release 2 (11.2.0.3) to 11g release 2 (11.2.0.4); from 11g release 2 (11.2.0.4) to 12c release 1 (12.1.0.2); and from 11g release 2 (11.2.0.4) or 12c release 1 (12.1.0.2) to 12c release 2 (12.2).

When you provision such software, Oracle Fleet Patching and Provisioning offers additional features for creating various types of databases (such as Oracle RAC, single instance, and Oracle Real Application Clusters One Node (Oracle RAC One Node) databases) on different types of storage, and other options, such as using templates and creating container databases (CDBs). The Oracle Fleet Patching and Provisioning Server can add nodes to an Oracle RAC configuration, and remove nodes from an Oracle RAC configuration. Oracle Fleet Patching and Provisioning also improves and makes more efficient patching of database software, allowing for rapid and remote patching of the software, in most cases, without any downtime for the database.

- *Support for single-instance databases:* You can use Oracle Fleet Patching and Provisioning to provision, patch, and upgrade single-instance databases running on clusters or Oracle Restart, or on single, standalone nodes.
- *Advanced patching capabilities:* When patching an Oracle Grid Infrastructure or Oracle Database home, Oracle Fleet Patching and Provisioning offers a batch mode that speeds the patching process by patching some or all nodes of a cluster in parallel, rather than sequentially.

For Oracle Database homes, you can define disjoint sets of nodes. Each set of nodes is updated sequentially. By defining sets with reference to the database instances running on them, you can minimize the impact of rolling updates by ensuring that services are never taken completely offline. A “smartmove” option is available to help define the sets of batches to meet this goal.

Integration with Application Continuity is another enhancement to help eliminate the impact of maintenance. This provides the ability to gracefully drain and relocate services within a cluster, completely masking the maintenance from users.

- *Notifications:* The Oracle Fleet Patching and Provisioning Server is the central repository for the software homes available to the data center. Therefore, it is essential that administrators throughout the data center be aware of changes to the inventory which might impact their areas of responsibility.

Oracle Fleet Patching and Provisioning enables you and other users to subscribe to image series events. Anyone subscribed will be notified by email of any changes to the images available in a particular image series. Also, users can be notified by email when a working copy of a gold image is added to or deleted from a client.

- *Custom workflow support:* You can create actions for various Oracle Fleet Patching and Provisioning operations, such as importing images, adding or deleting working copies of the gold images, and managing a software home. You can define different actions for each operation, and further differentiate by the type of image to which the operation applies. Actions that you define can be executed before or after the given operation, and are executed on the deployment the operation applies to, whether it is the Oracle Fleet Patching and Provisioning Server, a target that is not running an Oracle Fleet Patching and Provisioning Client, or a target that is running an Oracle Fleet Patching and Provisioning Client.
- *Resume failed operations:* If an operation, such as adding an image, provisioning a working copy of a gold image, or performing a scale, patch or upgrade fails, then Oracle Fleet Patching and Provisioning reports the error and stops. After the problem is corrected (for example, a directory permissions or ownership misconfiguration on a target node), you can rerun the RHPCTL command that failed, and it will resume from the point of failure. This avoids redoing any work that may have been completed prior to the failure.
- *Audit command:* The Oracle Fleet Patching and Provisioning Server records the execution of all Oracle Fleet Patching and Provisioning operations and also records their outcome (whether success or failure). An audit mechanism enables you to query the audit log in a variety of dimensions, and also to manage its contents and size.

 **Note:**

- Oracle does not support Oracle Fleet Patching and Provisioning on HP-UX or Windows operating systems.
- The Oracle Fleet Patching and Provisioning Server does not manage operating system images.

Oracle Fleet Patching and Provisioning Architecture

Conceptual information regarding Oracle Fleet Patching and Provisioning architecture.

Oracle Fleet Patching and Provisioning architecture consists of an Oracle Fleet Patching and Provisioning Server and any number of Oracle Fleet Patching and Provisioning Clients and targets. Oracle recommends deploying the Oracle Fleet Patching and Provisioning Server in a multi-node cluster so that it is highly available.

The Oracle Fleet Patching and Provisioning Server cluster is a repository for all data, of which there are primarily two types:

- Gold images
- Metadata related to users, roles, permissions, and identities

The Oracle Fleet Patching and Provisioning Server (FPPS) acts as a central server for provisioning Oracle Database homes, Oracle Grid Infrastructure homes, and other application software homes, making them available to the cluster hosting the Oracle Fleet Patching and Provisioning Server and to the Oracle Fleet Patching and Provisioning Client (FPPC) clusters and targets.

Users operate on the Oracle Fleet Patching and Provisioning Server or Oracle Fleet Patching and Provisioning Client to request deployment of Oracle homes or to query gold images. When a user makes a request for an Oracle home, specifying a gold image, the Oracle Fleet Patching and Provisioning Client communicates with the Oracle Fleet Patching and Provisioning Server to pass on the request. The Oracle Fleet Patching and Provisioning Server processes the request by taking appropriate action to instantiate a copy of the gold image, and to make it available to the Oracle Fleet Patching and Provisioning Client cluster using available technologies such as Oracle Automatic Storage Management Cluster File System (Oracle ACFS) and local file systems.

The Oracle Fleet Patching and Provisioning Server communicates with Oracle Fleet Patching and Provisioning Clients (running Oracle Grid Infrastructure 12c release 2 (12.2.0.1) or later), and targets (a target is an installation with Oracle Grid Infrastructure 12c release 1 (12.1.0.2) or release 11.2, or with no Oracle Grid Infrastructure installed) using the following ports, several of which you can configure, as described in [Table 1-1](#). Additionally, differences in ports used when communicating with Oracle Fleet Patching and Provisioning Clients versus targets are noted.

Table 1-1 Oracle Fleet Patching and Provisioning Communication Ports

Client, Target, or Both	Protocol	Port	Purpose	Description
Target	TCP	22	SSH	Authentication-based operations involving clientless targets.
Client	TCP	22	SSH	Provisioning of Oracle Grid Infrastructure 12c release 2 (12.2.0.1) or later requires an SSH port. (Subsequent Oracle Fleet Patching and Provisioning Server/Client interactions use the JMX path.)
REST API invocation node	HTTPS	8894	Oracle FPPS must allow incoming and outgoing communication from the REST invocation node REST request response	REST invocation node initiates a HTTPS connection to FPPS on this port. FPPS should allow an incoming connection and outgoing response to the REST Invocation node for the established connection.
Client	TCP	8896	JMX registry and server port	For establishing Oracle Fleet Patching and Provisioning Server communication with Oracle Fleet Patching and Provisioning Clients. You can configure this port using the <code>srvctl modify rhpserver -port port_number</code> command. Note: The preceding command requires you to restart the service.
Client	UDP	Port 53 must be open only on the FPPS to accept incoming connections from FPPC nodes and should allow outgoing communication, GNS response to be sent back FPPC.	GNS port	GNS is used for Oracle Fleet Patching and Provisioning Clients to locate the Oracle Fleet Patching and Provisioning Server. You can configure GNS with or without zone delegation.

Table 1-1 (Cont.) Oracle Fleet Patching and Provisioning Communication Ports

Client, Target, Protocol or Both	Port	Purpose	Description
Both	TCP	Specify one port for each RHPCTL command from ephemeral port range, or one port as specified with the <code>srvctl modify rhpserver -pl_port port_number</code> command. Progress listener port must be open to accept incoming connections on the server where RHPCTL is run (whether a Oracle Fleet Patching and Provisioning Server or Client).	Command progress listener Oracle Fleet Patching and Provisioning Server opens a random port from the ephemeral range to monitor progress on the client or target, or uses the fixed port you specify with the <code>srvctl modify rhpserver -pl_port port_number</code> and multiplexes across clients/targets.
Clients running Oracle Database 18c or Oracle Database 12c release 2 (12.2.0.1) with the January 2018 RU, or later	TCP	You must have six ports for gold image provisioning on an Oracle Fleet Patching and Provisioning Client server to accept incoming connections.	Gold image transfers to Oracle Database 18c clients and clients with the 2018 January RU (running the <code>rhpsctl add workingcopy</code> command on the Oracle Fleet Patching and Provisioning Server) Transferring copies of gold images from the Oracle Fleet Patching and Provisioning Server to clients uses six ports chosen from the ephemeral range, or six ports from the range you define using the <code>srvctl modify rhpserver -port_range port_number_range</code> . In this case, specify a range to accommodate the anticipated degree of parallelism (concurrent transfers) you will use. If the <code>port_range</code> value is specified and if RHPS manages 12.2 clients, then the client must be patched to 12.2.0.1.180717OCWJUL2018 RU or later.

Oracle Fleet Patching and Provisioning Server

The Oracle Fleet Patching and Provisioning Server (FPPS) is a highly available software provisioning system that uses Oracle Automatic Storage Management (Oracle ASM), Oracle Automatic Storage Management Cluster File System (Oracle ACFS), Grid Naming Service (GNS), and other components.

The Oracle Fleet Patching and Provisioning Server primarily acts as a central server for provisioning Oracle homes, making them available to Oracle Fleet Patching and Provisioning Client and targets.

Features of the Oracle Fleet Patching and Provisioning Server:

- Efficiently stores gold images and image series for the managed homes, including separate binaries, and metadata related to users, roles, and permissions.
- Provides a list of available homes to clients upon request.
- Patch a software home once and then deploy the home to any Oracle Fleet Patching and Provisioning Client or any other target, instead of patching every site.
- Provides the ability to report on existing deployments.
- Deploys homes on physical servers and virtual machines.
- Notifies subscribers of changes to image series.
- Maintains an audit log of all RHPCTL commands run.

Oracle Fleet Patching and Provisioning Targets

Computers of which Oracle Fleet Patching and Provisioning is aware are known as targets.

Oracle Fleet Patching and Provisioning Servers can create new targets, and can also install and configure Oracle Grid Infrastructure on targets with only an operating system installed. Subsequently, Oracle Fleet Patching and Provisioning Server can provision database and other software on those targets, perform maintenance, scale the target cluster, in addition to many other operations. All Oracle Fleet Patching and Provisioning commands are run on the Oracle Fleet Patching and Provisioning Server. Targets running the Oracle Fleet Patching and Provisioning Client in Oracle Clusterware 12c release 2 (12.2), and later, may also run many of the Oracle Fleet Patching and Provisioning commands to request new software from the Oracle Fleet Patching and Provisioning Server and initiate maintenance themselves, among other tasks.

Note:

The Oracle Fleet Patching and Provisioning Server communicates with Oracle Grid Infrastructure Clusters at version 12.2.0.1 and later through an Oracle Fleet Patching and Provisioning Client that can be configured and started up on the target cluster. The Oracle Fleet Patching and Provisioning Client is not supported for targets at Oracle Grid Infrastructure version 12.1 and earlier, on all versions of Oracle Restart and database standalone targets, such as database homes without an Oracle Grid Infrastructure home or Oracle Restart home.

Oracle Fleet Patching and Provisioning Clients

The Oracle Fleet Patching and Provisioning Client is part of the Oracle Grid Infrastructure. Users operate on an Oracle Fleet Patching and Provisioning Client to perform tasks such as requesting deployment of Oracle homes and listing available gold images.

When a user requests an Oracle home specifying a gold image, the Oracle Fleet Patching and Provisioning Client communicates with the Oracle Fleet Patching and Provisioning Server to pass on the request. The Oracle Fleet Patching and Provisioning Server processes the request by instantiating a working copy of the gold

image and making it available to the Oracle Fleet Patching and Provisioning Client using Oracle ACFS or a different local file system.

The Oracle Fleet Patching and Provisioning Client:

- Can use Oracle ACFS to store working copies of gold images which can be rapidly provisioned as local homes; new homes can be quickly created or undone using Oracle ACFS snapshots.

 **Note:**

Oracle supports using other local file systems besides Oracle ACFS.

- Provides a list of available homes from the Oracle Fleet Patching and Provisioning Server.
- Has full functionality in Oracle Clusterware 12c release 2 (12.2) and can communicate with Oracle Fleet Patching and Provisioning Servers from Oracle Clusterware 12c release 2 (12.2), or later.

Related Topics

- [Creating a Fleet Patching and Provisioning Client](#)
Users operate on a Fleet Patching and Provisioning Client to perform tasks such as requesting deployment of Oracle homes and querying gold images.

Authentication Options for Oracle Fleet Patching and Provisioning Operations

Some RHPCTL commands show authentication choices as an optional parameter.

Specifying an authentication option is not required when running an RHPCTL command on an Oracle Fleet Patching and Provisioning Client, nor when running an RHPCTL command on the Oracle Fleet Patching and Provisioning Server and operating on an Oracle Fleet Patching and Provisioning Client, because the server and client establish a trusted relationship when the client is created, and authentication is handled internally each time a transaction takes place. (The only condition for server/client communication under which an authentication option must be specified is when the server is provisioning a new Oracle Grid Infrastructure deployment—in this case, the client does not yet exist.)

To operate on a target that is not an Oracle Fleet Patching and Provisioning Client, you must provide the Oracle Fleet Patching and Provisioning Server with information allowing it to authenticate with the target. The options are as follows:

- Provide the `root` password (on `stdin`) for the target
- Provide the `sudo` user name, `sudo` binary path, and the password (`stdin`) for target
- Provide a password (either `root` or `sudouser`) non-interactively from local encrypted store (using the `-cred` authentication parameter)
- Provide a path to the identity file stored on the Oracle Fleet Patching and Provisioning Server for SSL-encrypted passwordless authentication (using the `-auth sshkey` option)

Passwordless Authentication Details

The Oracle Fleet Patching and Provisioning Server can authenticate to targets over SSH using a key pair. To enable this option, you must establish user equivalence between the `crsusr` on the Oracle Fleet Patching and Provisioning Server and `root` or a `sudouser` on the target.

Note:

The steps to create that equivalence are platform-dependent and so not shown in detail here. For Linux, see commands `ssh-keygen` to be run on the target and `ssh-copy-id` to be run on the Oracle Fleet Patching and Provisioning Server.

For example, assuming that you have established user equivalency between `crsusr` on the Oracle Fleet Patching and Provisioning Server and `root` on the target node, `nonRHPCClient4004.example.com`, and saved the key information on the Oracle Fleet Patching and Provisioning Server at `/home/oracle/rhp/ssh-key/key` `-path`, then the following command will provision a copy of the specified gold image to the target node with passwordless authentication:

```
$ rhpctl add workingcopy -workingcopy db12102_160607wc1 -image
db12102_160607
  -targetnode nonRHPCClient4004.example.com -path /u01/app/oracle/
12.1/rhp/dbhome_1
  -oraclebase /u01/app/oracle -auth sshkey -arg1 user:root -arg2
  identity_file:/home/oracle/rhp/ssh-key/key
```

For equivalency between `crsusr` on the Oracle Fleet Patching and Provisioning Server and a privileged user (other than `root`) on the target, the `-auth` portion of the command would be similar to the following:

```
-auth sshkey -arg1 user:ssh_user -arg2
identity_file:path_to_identity_file_on_RHPS
  -arg3 sudo_location:path_to_sudo_binary_on_target
```

Related Topics

- [rhpctl add credentials](#)
- [rhpctl delete credentials](#)
- [rhpctl add workingcopy](#)
Creates a working copy on a client cluster.

Oracle Fleet Patching and Provisioning Roles

An administrator assigns roles to Oracle Fleet Patching and Provisioning users with access-level permissions defined for each role. Users on Oracle Fleet Patching and Provisioning Clients are also assigned specific roles. Oracle Fleet Patching and Provisioning includes basic built-in and composite built-in roles.

Basic Built-In Roles

The basic built-in roles and their functions are:

- **GH_ROLE_ADMIN:** An administrative role for everything related to roles. Users assigned this role are able to run `rhpcctl verb role` commands.
- **GH_SITE_ADMIN:** An administrative role for everything related to Oracle Fleet Patching and Provisioning Clients. Users assigned this role are able to run `rhpcctl verb client` commands.
- **GH_SERIES_ADMIN:** An administrative role for everything related to image series. Users assigned this role are able to run `rhpcctl verb series` commands.
- **GH_SERIES_CONTRIB:** Users assigned this role can add images to a series using the `rhpcctl insertimage series` command, or delete images from a series using the `rhpcctl deleteimage series` command.
- **GH_WC_ADMIN:** An administrative role for everything related to working copies of gold images. Users assigned this role are able to run `rhpcctl verb workingcopy` commands.
- **GH_WC_OPER:** A role that enables users to create a working copy of a gold image for themselves or others using the `rhpcctl add workingcopy` command with the `-user` option (when creating for others). Users assigned this role do not have administrative privileges and can only administer the working copies of gold images that they create.
- **GH_WC_USER:** A role that enables users to create a working copy of a gold image using the `rhpcctl add workingcopy` command. Users assigned this role do not have administrative privileges and can only delete working copies that they create.
- **GH_IMG_ADMIN:** An administrative role for everything related to images. Users assigned this role are able to run `rhpcctl verb image` commands.
- **GH_IMG_USER:** A role that enables users to create an image using the `rhpcctl add | import image` commands. Users assigned this role do not have administrative privileges and can only delete images that they create.
- **GH_IMG_TESTABLE:** A role that enables users to add a working copy of an image that is in the `TESTABLE` state. Users assigned this role must also be assigned either the `GH_WC_ADMIN` role or the `GH_WC_USER` role to add a working copy.
- **GH_IMG_RESTRICT:** A role that enables users to add a working copy from an image that is in the `RESTRICTED` state. Users assigned this role must also be assigned either the `GH_WC_ADMIN` role or the `GH_WC_USER` role to add a working copy.
- **GH_IMG_PUBLISH:** Users assigned this role can promote an image to another state or retract an image from the `PUBLISHED` state to either the `TESTABLE` or `RESTRICTED` state.
- **GH_IMG_VISIBILITY:** Users assigned this role can modify access to promoted or published images using the `rhpcctl allow | disallow image` commands.
- **GH_AUTHENTICATED_USER:** Users assigned to this role can execute any operation in an Oracle Fleet Patching and Provisioning Client.

- **GH_CLIENT_ACCESS:** Any user created automatically inherits this role. The `GH_CLIENT_ACCESS` role includes the `GH_AUTHENTICATED_USER` built-in role.
- **GH_ROOT_UA_CREATE:** A role that enables users to create a root user action. Users assigned this role can run the `rhpcctl add useraction` command with the `-runasroot` option.
- **GH_ROOT_UA_ASSOCIATE:** A role that enables users to associate a root user action with the `-imagetype` option. Users assigned this role can associate an existing root user action to an image type.
- **GH_ROOT_UA_USE:** A role that enables users to execute a root user action within the operation selected at user action creation.

Composite Built-In Roles

The composite built-in roles and their functions are:

- **GH_SA:** The Oracle Grid Infrastructure user on an Oracle Fleet Patching and Provisioning Server automatically inherits this role.

The `GH_SA` role includes the following basic built-in roles: `GH_ROLE_ADMIN`, `GH_SITE_ADMIN`, `GH_SERIES_ADMIN`, `GH_SERIES_CONTRIB`, `GH_WC_ADMIN`, `GH_IMG_ADMIN`, `GH_IMG_TESTABLE`, `GH_IMG_RESTRICT`, `GH_IMG_PUBLISH`, and `GH_IMG_VISIBILITY`.
- **GH_CA:** The Oracle Grid Infrastructure user on an Oracle Fleet Patching and Provisioning Client automatically inherits this role.

The `GH_CA` role includes the following basic built-in roles: `GH_SERIES_ADMIN`, `GH_SERIES_CONTRIB`, `GH_WC_ADMIN`, `GH_IMG_ADMIN`, `GH_IMG_TESTABLE`, `GH_IMG_RESTRICT`, `GH_IMG_PUBLISH`, and `GH_IMG_VISIBILITY`.
- **GH_OPER:** This role includes the following built-in roles: `GH_WC_OPER`, `GH_SERIES_ADMIN`, `GH_IMG_TESTABLE`, `GH_IMG_RESTRICT`, and `GH_IMG_USER`. Users assigned this role can delete only images that they have created.

Consider a gold image called `G1` that is available on the Oracle Fleet Patching and Provisioning Server.

Further consider that a user, `U1`, on an Oracle Fleet Patching and Provisioning Client, `CL1`, has the `GH_WC_USER` role. If `U1` requests to provision an Oracle home based on the gold image `G1`, then `U1` can do so, because of the permissions granted by the `GH_WC_USER` role. If `U1` requests to delete `G1`, however, then that request would be denied because the `GH_WC_USER` role does not have the necessary permissions.

The Oracle Fleet Patching and Provisioning Server can associate user-role mappings to the Oracle Fleet Patching and Provisioning Client. After the Oracle Fleet Patching and Provisioning Server delegates user-role mappings, the Oracle Fleet Patching and Provisioning Client can then modify user-role mappings on the Oracle Fleet Patching and Provisioning Server for all users that belong to the Oracle Fleet Patching and Provisioning Client site. This is implied by the fact that only the Oracle Fleet Patching and Provisioning Server qualifies user IDs from an Oracle Fleet Patching and Provisioning Client site with the client cluster name of that site. Thus, the Oracle Fleet Patching and Provisioning Client `CL1` will not be able to update user mappings of a user on `CL2`, where `CL2` is the cluster name of a different Oracle Fleet Patching and Provisioning Client.

Oracle Fleet Patching and Provisioning Images

By default, when you create a gold image using either `rhpctl import image` or `rhpctl add image`, the image is ready to provision working copies. However, under certain conditions, you may want to restrict access to images and require someone to test or validate the image before making it available for general use.

You can also create a set of gold images on the Oracle Fleet Patching and Provisioning Server that can be collectively categorized as a gold image series which relate to each other, such as identical release versions, gold images published by a particular user, or images for a particular department within an organization.

Related Topics

- [Image State](#)
- [Image Series](#)
An image series is a convenient way to group different gold images into a logical sequence.
- [Image Type](#)
When you add or import a gold image, you must specify an image type.

Gold Image Distribution Among Oracle Fleet Patching and Provisioning Servers

Oracle Fleet Patching and Provisioning can automatically share and synchronize gold images between Oracle Fleet Patching and Provisioning Servers.

In the Oracle Fleet Patching and Provisioning architecture, one Oracle Fleet Patching and Provisioning Server manages a set of Oracle Fleet Patching and Provisioning Clients and targets within a given data center or network segment of a data center. If you have more than one data center or a segmented data center, you must have more than one Oracle Fleet Patching and Provisioning Server.

In the Oracle Fleet Patching and Provisioning architecture, one Oracle Fleet Patching and Provisioning Server manages a set of Oracle Fleet Patching and Provisioning Clients and targets within a given data center or network segment of a data center. If you have more than one data center or a segmented data center, then you must have more than one Oracle Fleet Patching and Provisioning Server to facilitate large-scale standardization across multiple estates.

Oracle Fleet Patching and Provisioning Servers retain the ability to create and manage gold images private to their scope, so local customizations are seamlessly supported.

You must first establish a peer relationship between two Oracle Fleet Patching and Provisioning Servers. Registration uses the names of the Oracle Fleet Patching and Provisioning Server clusters. The names of the two clusters can be the same but there is one naming restriction: an Oracle Fleet Patching and Provisioning Server, such as `FPPS_1`, cannot register a peer Oracle Fleet Patching and Provisioning Server if that peer has the same name as an Oracle Fleet Patching and Provisioning Client or target within the management domain of `FPPS_1`.

The following steps show how you can establish a peer relationship between two Oracle Fleet Patching and Provisioning Servers. Note that super user or root credentials are not required in this process.

1. On the first Oracle Fleet Patching and Provisioning Server (FPPS_1), create a file containing the server configuration information.

```
$ rhpctl export server -serverdata file_path
```

2. Copy the server configuration file created on FPPS_1 to a second Oracle Fleet Patching and Provisioning Server (FPPS_2).
3. On the second Oracle Fleet Patching and Provisioning Server (FPPS_2), complete the registration of FPPS_2.

```
$ rhpctl register server -server FPPS_1_cluster_name  
-serverdata server_cfg_file_copied_from_FPPS_1
```

4. On FPPS_2, create a file containing the server configuration information.

```
$ rhpctl export server -serverdata file_path
```

5. Copy the server configuration file created on FPPS_2 to FPPS_1.
6. On the first Oracle Fleet Patching and Provisioning Server (FPPS_1), complete the registration of FPPS_1.

```
$ rhpctl register server -server FPPS_2_cluster_name  
-serverdata server_cfg_file_copied_from_FPPS_2
```

After you register an Oracle Fleet Patching and Provisioning Server as a peer, the following command displays the peer (or peers) of the server:

```
$ rhpctl query peerserver
```

You can inspect the images on a peer Oracle Fleet Patching and Provisioning Server, as follows:

```
$ rhpctl query image -server server_cluster_name
```

The preceding command displays all images on a specific peer Oracle Fleet Patching and Provisioning Server. Additionally, you can specify a peer server along with the `-image image_name` parameter to display details of a specific image on a specific peer server.

An Oracle Fleet Patching and Provisioning Server can have multiple peers. Oracle does not support chained relationships between peers, however, such as, if FPPS_1 is a peer of FPPS_2, and FPPS_2 is also a peer of FPPS_3, then no relationship is established or implied between FPPS_1 and FPPS_3, although you can make them peers if you want.

Retrieve a copy or copies of gold images from a peer Oracle Fleet Patching and Provisioning Server, as follows:

```
$ rhpctl instantiate image -server server_cluster_name
```

Running the `rhpctl instantiate image` command activates an auto-update mechanism. From that point on, when you create gold images on a peer Oracle Fleet Patching and Provisioning Server, such as `FPPS_2`, they are candidates for being automatically copied to the Oracle Fleet Patching and Provisioning Server that performed the instantiate operation, such as `FPPS_1`. Whether a new gold image is automatically copied depends on that relevance of the image to any instantiate parameters that you may include in the command:

- `-all`: Creates an automatic push for all gold images created on `FPPS_2` to `FPPS_1`
- `-image image_name`: Creates an automatic push for all new descendant gold images of the named image created on `FPPS_2` to `FPPS_1`. A descendant of the named image is an image that is created on `FPPS_2` using the `rhpctl add image` command.
- `-series series_name`: Creates an automatic push for all gold images added to the named series on `FPPS_2` to `FPPS_1`
- `-imagetype image_type`: Creates an automatic push for all gold images created of the named image type on `FPPS_2` to `FPPS_1`

To stop receiving updates that were established by the `rhpctl instantiate image` command, run `rhpctl uninstantiate image` and specify the peer Oracle Fleet Patching and Provisioning Server and one of the following: all, image name, image series name, or image type.

End the peer relationship, as follows, on any one of the Oracle Fleet Patching and Provisioning Servers:

```
$ rhpctl unregister server -server server_cluster_name
```

Related Topics

- [rhpctl export server](#)
- [rhpctl register server](#)
- [rhpctl query peerserver](#)
- [rhpctl query image](#)
- [rhpctl instantiate image](#)
- [rhpctl uninstantiate image](#)
- [rhpctl unregister server](#)



See Also:

[Propagating Images Between Fleet Patching and Provisioning Servers](#)

Oracle Fleet Patching and Provisioning Server Auditing

The Oracle Fleet Patching and Provisioning Server records the execution of all Oracle Fleet Patching and Provisioning operations, and also records whether those operations succeeded or failed.

An audit mechanism enables administrators to query the audit log in a variety of dimensions, and also to manage its contents and size.

Oracle Fleet Patching and Provisioning Notifications

The Oracle Fleet Patching and Provisioning Server is the central repository for the software homes available to the data center. Therefore, it is essential for administrators throughout the data center to be aware of changes to the inventory that may impact their areas of responsibility.

You can create subscriptions to image series events. Oracle Fleet Patching and Provisioning notifies a subscribed role or number of users by email of any changes to the images available in the series, including addition or removal of an image. Each series may have a unique group of subscribers.

Also, when a working copy of a gold image is added to or deleted from a target, the owner of the working copy and any additional users can be notified by email. If you want to enable notifications for additional Oracle Fleet Patching and Provisioning events, you can create a user-defined action as described in the next section.

Oracle Fleet Patching and Provisioning Implementation

Implementing Oracle Fleet Patching and Provisioning involves creating an Oracle Fleet Patching and Provisioning Server, adding gold images to the server, and creating working copies of gold images to provision software.

After you install and configure Oracle Clusterware, you can configure and start using Oracle Fleet Patching and Provisioning. You must create an Oracle Fleet Patching and Provisioning Server where you create and store gold images of database and other software homes.

Creating a Fleet Patching and Provisioning Server

The Fleet Patching and Provisioning Server uses a repository that you create in an Oracle ACFS file system in which you store all the software homes that you want to make available to clients and targets.

To create a Fleet Patching and Provisioning Server:

1. Use the Oracle ASM configuration assistant (ASMCA) to create an Oracle ASM disk group on the Fleet Patching and Provisioning Server to store software, as follows:

```
$ Grid_home/bin/asmca
```

Because this disk group is used to store software, Oracle recommends a minimum of 50 GB for this disk group.

 **Note:**

You must set Oracle ASM Dynamic Volume Manager (Oracle ADVM) compatibility settings for this disk group to 12.1.

2. Provide a mount path that exists on all nodes of the cluster. The Fleet Patching and Provisioning Server uses this path to mount gold images.

```
$ mkdir -p storage_path/images
```

3. As root, create the Fleet Patching and Provisioning Server resource, as follows:

```
# Grid_home/bin/srvctl add rhpserver -storage storage_path  
-diskgroup disk_group_name
```

4. Start the Fleet Patching and Provisioning Server, as follows:

```
$ Grid_home/bin/srvctl start rhpserver
```

After you start the Fleet Patching and Provisioning Server, use the Fleet Patching and Provisioning Control (RHPCTL) utility to further manage Fleet Patching and Provisioning.

Related Topics

- *Oracle Automatic Storage Management Administrator's Guide*
- [Oracle Fleet Patching and Provisioning Control \(RHPCTL\) Command Reference](#)
Use the Oracle Fleet Patching and Provisioning Control (RHPCTL) utility to manage Oracle Fleet Patching and Provisioning in your cluster.

Adding Gold Images to the Fleet Patching and Provisioning Server

Use RHPCTL to add gold images for later provisioning of software.

The Fleet Patching and Provisioning Server stores and serves gold images of software homes. These images must be instantiated on the Fleet Patching and Provisioning Server.

 **Note:**

Images are read-only, and you cannot run programs from them. To create a usable software home from an image, you must create a working copy of a gold image. You cannot directly use images as software homes. You can, however, use images to create working copies (software homes).

You can import software to the Fleet Patching and Provisioning Server using any one of the following methods:

- You can import an image from an installed home on the Fleet Patching and Provisioning Server using the following command:

```
rhpcctl import image -image image_name -path path_to_installed_home
  [-imagetype ORACLEDBSOFTWARE | ORACLEGISOFTWARE |
  ORACLEGGSOFTWARE | SOFTWARE]
```

ORACLEDBSOFTWARE is the default if `-imagetype` is not specified.

- You can import an image from an installed home on a Fleet Patching and Provisioning Client, using the following command run from the Fleet Patching and Provisioning Client:

```
rhpcctl import image -image image_name -path path_to_installed_home
```

- You can create an image from an existing working copy using the following command:

```
rhpcctl add image -image image_name -workingcopy working_copy_name
```

Use the first two commands in the preceding list to seed the image repository, and to add additional images over time. Use the third command on the Oracle Fleet Patching and Provisioning Server as part of the workflow for creating a gold image that includes patches applied to a pre-existing gold image.

The preceding three commands also create an Oracle ACFS file system in the Oracle Fleet Patching and Provisioning root directory, similar to the following:

```
/u01/rhp/images/images/RDBMS_121020617524
```

Related Topics

- [Patching Oracle Database Software](#)
To patch an Oracle database, you move the database home to a new home, which includes the patches you want to implement.
- [RHPCTL Command Reference](#)
This section describes RHPCTL command usage information, and lists and describes RHPCTL commands.

Image State

You can set the state of an image to `TESTABLE` or `RESTRICTED` so that only users with the `GH_IMG_TESTABLE` or `GH_IMG_RESTRICT` roles can provision working copies from this image. Once the image has been tested or validated, you can change the state and make the image available for general use by running the `rhpcctl promote image -image image_name -state PUBLISHED` command. The default image state is `PUBLISHED` when you add a new gold image, but you can optionally specify a different state with the `rhpcctl add image` and `rhpcctl import image` commands.

Image Series

An image series is a convenient way to group different gold images into a logical sequence.

Fleet Patching and Provisioning treats each image as an independent entity with respect to other images. No relationship is assumed between images, even if they follow some specific nomenclature. The image administrator may choose to name images in a logical manner that makes sense to the user community, but this does not create any management grouping within the Fleet Patching and Provisioning framework.

Use the `rhpcctl add series` command to create an image series and associate one or more images to this series. The list of images in an image series is an ordered list. Use the `rhpcctl insertimage series` and `rhpcctl deleteimage series` to add and delete images in an image series. You can also change the order of images in a series using these commands.

The `insertimage` and `deleteimage` commands do not instantiate or delete actual gold images but only change the list. Also, an image can belong to more than one series (or no series at all).

Image Type

When you add or import a gold image, you must specify an image type.

Oracle Clusterware provides the following built-in base image types:

```
ORACLEDBSOFTWARE
ORACLEGISoftware
ORACLEGGSoftware
SOFTWARE
```

Every gold image must have an image type, and you can create your own image types. A new image type must be based on one of the built-in types. The image type directs Fleet Patching and Provisioning to apply its capabilities for managing Oracle Grid Infrastructure and Oracle Database homes. Fleet Patching and Provisioning also uses image type to organize the custom workflow support framework.

Creating a Custom Image Type

Use the `rhpcctl add imagetype` command to create custom image types.

For example, to create an image type called `DBTEST`, which is based on the `ORACLEDBSOFTWARE` image type:

```
$ rhpcctl add imagetype -imagetype DBTEST -basetype ORACLEDBSOFTWARE
```



Note:

When you create an image type that is based on an existing image type, the new image type does not inherit any user actions (for custom workflow support) from the base type.

Provisioning Copies of Gold Images

Use RHPCTL to provision copies of gold images to Fleet Patching and Provisioning Servers, Clients, and targets.

After you create and import a gold image, you can provision software by adding a copy of the gold image (called a working copy) on the Fleet Patching and Provisioning Server, on a Fleet Patching and Provisioning Client, or a target. You can run the software provisioning command on either the Server or a Client.

- To create a working copy on the Fleet Patching and Provisioning Server:

```
$ rhpctl add workingcopy -workingcopy working_copy_name -image  
image_name
```

- To create a working copy in a local file system on a Fleet Patching and Provisioning Client:

```
$ rhpctl add workingcopy -workingcopy working_copy_name -image  
image_name  
-storagetype LOCAL -path path_to_software_home
```

- To create a working copy on a Fleet Patching and Provisioning Client from the Fleet Patching and Provisioning Server:

```
$ rhpctl add workingcopy -workingcopy working_copy_name -image  
image_name  
-client client_cluster_name
```

Note:

- The directory you specify in the `-path` parameter must be empty.
- You can re-run the provisioning command in case of an interruption or failure due to system or user errors. After you fix the reported errors, re-run the command and it will resume from the point of failure.

Related Topics

- [Storage Options for Provisioned Software](#)
Choose one of three storage options where Fleet Patching and Provisioning stores working copies of gold images.

User Group Management in Fleet Patching and Provisioning

When you create a working copy of a gold image as part of a move or upgrade operation, Fleet Patching and Provisioning configures the operating system groups in the new working copy to match those of the source software home.

These operating system groups are used for operating system authentication, such as OSDBA and OSOPER. Oracle FPP configures operating system groups for both unmanaged and managed software homes from which you move or upgrade.

When you create a gold image of SOFTWARE image type, any user groups in the source are not inherited and images of this type never contain user group information. When you provision a working copy from a SOFTWARE gold image using the `rhptcl add workingcopy` command, you can, optionally, configure user groups in the working copy using the `-groups` parameter.

The `rhptcl move database`, `rhptcl move gihome`, `rhptcl upgrade database`, and `rhptcl upgrade gihome` commands all require you to specify a source home (either an unmanaged home or a managed home (working copy) that you provisioned using Fleet Patching and Provisioning), and a destination home (which must be a working copy).

When you have provisioned the destination home using the `rhptcl add workingcopy` command, prior to performing a move or upgrade operation, you must ensure that the groups configured in the source home match those in the destination home. Fleet Patching and Provisioning configures the groups as part of the add operation.

When you create a gold image of either the ORACLEGISOFTWARE or the ORACLEDBSOFTWARE image type from a source software home (using the `rhptcl import image` command) or from a working copy (using the `rhptcl add image` command), the gold image inherits the Oracle user groups that were configured in the source. You cannot override this feature.

You can define user groups for ORACLEGISOFTWARE and ORACLEDBSOFTWARE working copies using the `rhptcl add workingcopy` command, depending on the image type and user group, as discussed in the subsequent sections.

This section describes how Fleet Patching and Provisioning manages user group configuration, and how the `-groups` command-line option of `rhptcl add workingcopy` functions.

ORACLEGISOFTWARE (Oracle Grid Infrastructure 11g release 2 (11.2), and 12c release 1 (12.1) and release 2 (12.2))

When you provision an Oracle Grid Infrastructure working copy of a gold image, the groups are set in the working copy according to the type of provisioning (whether regular provisioning or software only, and with or without the `-local` parameter), and whether you specify the `-groups` parameter with `rhptcl add workingcopy`. You can define OSDBA and OSASM user groups in Oracle Grid Infrastructure software with either the `-softwareonly` command parameter or by using a response file with the `rhptcl add workingcopy` command.

If you are provisioning only the Oracle Grid Infrastructure software using the `-softwareonly` command parameter, then you cannot use the `-groups` parameter, and Fleet Patching and Provisioning obtains OSDBA and OSASM user group information from the active Grid home.

If you use the `-local` command parameter (which is only valid when you use the `-softwareonly` command parameter) with `rhptcl add workingcopy`, then Fleet Patching and Provisioning takes the values of the groups from the command line (using the `-groups` parameter) or uses the default values, which Fleet Patching and Provisioning obtains from the `osdbagrps` binary of the gold image.

If none of the preceding applies, then Fleet Patching and Provisioning uses the installer default user group.

If you are provisioning and configuring a working copy using information from a response file, then Fleet Patching and Provisioning:

1. Uses the value of the user group from the command line, if provided, for OSDBA or OSASM, or both.
2. If you provide no value on the command line, then Fleet Patching and Provisioning retrieves the user group information defined in the response file.

If you are defining the OSOPER Oracle group, then, again, you can either use the `-softwareonly` command parameter or use a response file with the `rhctl add workingcopy` command.

If you use the `-softwareonly` command parameter, then you can provide the value on the command line (using the `-groups` parameter) or leave the user group undefined.

If you are provisioning and configuring a working copy of a gold image using information from a response file, then you can provide the value on the command line, use the information contained in the response file, or leave the OSOPER Oracle group undefined.

ORACLEDBSOFTWARE (Oracle Database 11g release 2 (11.2), and 12c release 1 (12.1) and release 2 (12.2))

If you are provisioning a working copy of Oracle Database software and you want to define Oracle groups, then use the `-groups` command parameter with the `rhctl add workingcopy` command. Oracle groups available in the various Oracle Database releases are as follows:

- Oracle Database 11g release 2 (11.2)
 - OSDBA
 - OSOPER
- Oracle Database 12c release 1 (12.1)
 - OSDBA
 - OSOPER
 - OSBACKUP
 - OSDG
 - OSKM
- Oracle Database 12c release 2 (12.2) and later
 - OSDBA
 - OSOPER
 - OSBACKUP
 - OSDG
 - OSKM
 - OSRAC

Regardless of which of the preceding groups you are defining (except for OSOPER), Fleet Patching and Provisioning takes the values of the groups from the command line (using the `-groups` parameter) or uses the default values, which Fleet Patching and Provisioning obtains from the `osdbagrps` binary of the gold image.

If any group picked up from the `osdbagrp` binary is not in the list of groups to which the database user belongs (given by the `id` command), then Fleet Patching and Provisioning uses the installer default user group. Otherwise, the database user is the user running the `rhctl add workingcopy` command.

Storage Options for Provisioned Software

Choose one of three storage options where Fleet Patching and Provisioning stores working copies of gold images.

When you provision software using the `rhctl add workingcopy` command, you can choose from three storage options where Fleet Patching and Provisioning places that software:

- In an Oracle ACFS shared file system managed by Fleet Patching and Provisioning (for database homes only)
- In a local file system not managed by Fleet Patching and Provisioning

Using the `rhctl add workingcopy` command with the `-storagetype` and `-path` parameters, you can choose where you store provisioned working copies. The applicability of the parameters depends on whether the node (or nodes) to which you are provisioning the working copy is a Fleet Patching and Provisioning Server, Fleet Patching and Provisioning Client, or a non-Fleet Patching and Provisioning client. You can choose from the following values for the `-storagetype` parameter:

- `RHP_MANAGED`: Choosing this value, which is available for Fleet Patching and Provisioning Servers and Fleet Patching and Provisioning Clients, stores working copies in an Oracle ACFS shared file system. The `-path` parameter is not used with this option because Fleet Patching and Provisioning manages the storage option.

Notes:

- You cannot store Oracle Grid Infrastructure homes in `RHP_MANAGED` storage.
 - Oracle recommends using the `RHP_MANAGED` storage type, which is available on Fleet Patching and Provisioning Servers, and on Clients configured with an Oracle ASM disk group.
 - If you provision working copies on a Fleet Patching and Provisioning Server, then you do not need to specify the `-storagetype` option because it will default to `RHP_MANAGED`.
 - If you choose to provision working copies on a Fleet Patching and Provisioning Client, and you do not specify the `-path` parameter, then the storage type defaults to `RHP_MANAGED` only if there is an Oracle ASM disk group on the client. Otherwise the command will fail. If you specify a location on the client for the `-path` parameter, then the storage type defaults to `LOCAL` with or without an Oracle ASM disk group.
- `LOCAL`: Choosing this value stores working copies in a local file system that is not managed by Fleet Patching and Provisioning.

When adding a database working copy, specifying a path is optional. If a path is not specified, then a path under `ORACLE_BASE` is automatically chosen. This path is displayed on the terminal.

In cases where you specify the `-path` parameter, if the file system is shared among all of the nodes in the cluster, then the working copy gets created on this shared storage. If the file system is not shared, then the working copy gets created in the location of the given path on every node in the cluster.

 **Note:**

The directory you specify in the `-path` parameter must be empty.

Related Topics

- [rhpctl add workingcopy](#)
Creates a working copy on a client cluster.

Provisioning for a Different User

If you want a different user to provision software other than the user running the command, then use the `-user` parameter of the `rhpctl add workingcopy` command.

 **Note:**

The default user is the user as which the RHPCTL command is being run.

When the provisioning is completed, all files and directories of the provisioned software are owned by the user you specified. Permissions on files on the remotely provisioned software are the same as the permissions that existed on the gold image from where you provisioned the application software.

Propagating Images Between Fleet Patching and Provisioning Servers

With automatic image propagation, you can set up automated copies of software images across different peer Fleet Patching and Provisioning Servers. Gold images that you register at one site are copied to peer Fleet Patching and Provisioning Servers.

In a peer-to-peer relationship between two Oracle Fleet Patching and Provisioning Servers, one server is the source for software images and the other is the destination for software images.

The criteria for copying software images between servers can be based on certain policies, such as software image type, image series, or all software images. When you register an image that meets the criteria for software image propagation, a copy of this image propagates to all registered peer servers.

The following example procedure establishes a relationship between two Fleet Patching and Provisioning Server sites, `FPPS-A` and `FPPS-B`, where `FPPS-A` is the source and `FPPS-B` is the destination for software images.

1. Run the following command on `FPPS-B`:

```
$ rhpctl export server -server FPPS-A -serverdata file_path
```

The preceding command creates a file named `FPPS-B.xml` in the directory path you specify for the `-serverdata` parameter.

2. Run the following command to register a peer server to the current Fleet Patching and Provisioning Server:

```
$ rhpctl register server -server FPPS-B -serverdata /tmp/FPPS-B.xml
```

The preceding command copies the `FPPS-B.xml` file that was created in the previous step to a location on the server where you run the command, which is `/tmp/FPPS-B.xml`, in this case.

The cluster in which you run the preceding command is the source site, and the server that you specify on the command line is the destination site to which software images are copied.

Use the `rhpctl unregister server` command to remove the peer-to-peer relationship.

3. Run the following command on `FPPS-B` to propagate software images from `FPPS-A` to `FPPS-B`:

```
$ rhpctl instantiate image -server FPPS-A -all
```

The preceding command propagates all images from `FPPS-A` to `FPPS-B`. If an image already exists on `FPPS-B`, then it is not propagated again.

 **Note:**

Propagation of images is based on the image name. RHPCTL does not compare the content of the images to determine whether they are different. If an image you want to propagate has a non-unique name, then RHPCTL assumes that the images are identical and does not propagate the image.

The image propagation is asynchronous and the propagation may not be immediate. You can check using `rhpctl query image` on the target.

Use the `rhpctl unstantiate image` command to cancel the propagation of a particular image. Any propagation already in progress is not affected by this command, and will continue until complete. The `-all` parameter removes any values for the `-imagetype` and `-series` parameters.

Related Topics

- [rhpctl export server](#)
- [rhpctl register server](#)
- [rhpctl unregister server](#)

- [rhpctl instantiate image](#)
- [rhpctl unstantiate image](#)



See Also:

[Gold Image Distribution Among Oracle Fleet Patching and Provisioning Servers](#)

2

Managing Oracle Grid Infrastructure and Database Software

This chapter includes the following topics:

- [Patching Oracle Grid Infrastructure and Oracle Database Using Batches](#)
- [Oracle Grid Infrastructure Management](#)
- [Oracle Database Software Management](#)
- [Combined Oracle Exadata Database Node and Grid Infrastructure Patching](#)
- [Zero-Downtime Upgrade](#)
- [Persistent Home Path During Patching](#)
- [User-Defined Actions](#)
- [Job Scheduler for Operations](#)
- [Oracle Restart Patching and Upgrading](#)

Patching Oracle Grid Infrastructure and Oracle Database Using Batches

You can sequentially process batches of nodes, with a number of nodes in each batch being restarted in parallel.

Using batches maximizes service availability during the patching process. When you patch Oracle Grid Infrastructure 12c release 2 (12.2.x) or later software homes, you can define the batches on the command line or choose to have Fleet Patching and Provisioning generate the list of batches based on its analysis of the database services running in the cluster.

There are several methods for defining batches:

- [User-Defined Batches](#)
- [Fleet Patching and Provisioning-Defined Batches](#)
- [Patching Oracle Database Using Batches](#)
- [Adaptive Oracle RAC-Rolling Patching for OJVM Deployments](#)

User-Defined Batches

When you use this method of patching, the first time you run the `ohpctl move gihome` command, you must specify the source home, the destination home, the batches, and other options, as needed. The command terminates after the first node restarts.

To patch Oracle Grid Infrastructure using batches that you define:

1. Define a list of batches on the command line and begin the patching process, as in the following example:

```
$ rhpctl move gihome -sourcewc wc1 -destwc wc2 -batches "(n1),  
(n2,n3),(n4)"
```

The preceding command example initiates the move operation, and terminates and reports successful when the Oracle Grid Infrastructure stack restarts in the first batch. Oracle Grid Infrastructure restarts the batches in the order you specified in the `-batches` parameter.

In the command example, node `n1` forms the first batch, nodes `n2` and `n3` form the second batch, and node `n4` forms the last batch. The command defines the source working copy as `wc1` and the patched (destination) working copy as `wc2`.

Notes:

You can specify batches such that singleton services (policy-managed singleton services or administrator-managed services running on one instance) are relocated between batches and non-singleton services remain partially available during the patching process.

2. You must process the next batch by running the `rhpctl move gihome` command, again, as follows:

```
$ rhpctl move gihome -destwc wc2 -continue
```

The preceding command example restarts the Oracle Grid Infrastructure stack on the second batch (nodes `n2` and `n3`). The command terminates by reporting that the second batch was successfully patched.

3. Repeat the previous step until you have processed the last batch of nodes. If you attempt to run the command with the `-continue` parameter after the last batch has been processed, then the command returns an error.

If the `rhpctl move gihome` command fails at any time during the above sequence, then, after determining and fixing the cause of the failure, rerun the command with the `-continue` option to attempt to patch the failed batch. If you want to skip the failed batch and continue with the next batch, use the `-continue` and `-skip` parameters. If you attempt to skip over the last batch, then the move operation is terminated.

Alternatively, you can reissue the command using the `-revert` parameter to undo the changes that have been made and return the configuration to its initial state.

You can use the `-abort` parameter instead of the `-continue` parameter at any point in the preceding procedure to terminate the patching process and leave the cluster in its current state.

 **Notes:**

- Policy-managed services hosted on a server pool with one active server, and administrator-managed services with one preferred instance and no available instances cannot be relocated and will go OFFLINE while instances are being restarted.
- If a move operation is in progress, then you cannot initiate another move operation from the same source home or to the same destination home.
- After the move operation has ended, services may be running on nodes different from the ones they were running on before the move and you will have to manually relocate them back to the original instances, if necessary.
- If you use the `-abort` parameter to terminate the patching operation, then Fleet Patching and Provisioning does not clean up or undo any of the patching steps. The cluster, databases, or both may be in an inconsistent state because all nodes are not patched.
- Depending on the start dependencies, services that were offline before the move began could come online during the move.

Fleet Patching and Provisioning-Defined Batches

Using Fleet Patching and Provisioning to define and patch batches of nodes means that you need only run one command, as shown in the following command example, where the source working is `wc1` and the destination working copy is `wc2`:

```
$ rhpctl move gihome -sourcewc wc1 -destwc wc2 -smartmove -saf 50 [-eval]
```

There is no need for you to do anything else unless you used the `-separate` parameter with the command. In that case, the move operation waits for user intervention to proceed to the next batch, and then you will have to run the command with the `-continue` parameter after each batch completes.

If the move operation fails at some point before completing, then you can either rerun the operation by running the command again, or you can undo the partially completed operation, as follows:

```
$ rhpctl move gihome -destwc destination_workingcopy_name -revert [authentication_option]
```

You can use the `-revert` parameter with an un-managed home.

The parameters used in the preceding example are as follows:

- `-smartmove`: This parameter restarts the Oracle Grid Infrastructure stack on disjoint sets of nodes so that singleton resources are relocated before Oracle Grid Infrastructure starts.

 **Note:**

If the server pool to which a resource belongs contains only one active server, then that resource will go offline as relocation cannot take place.

The `-smartmove` parameter:

- Creates a map of services and nodes on which they are running.
- Creates batches of nodes. The first batch will contain only the Hub node, if the configuration is an Oracle Flex Cluster. For additional batches, a node can be merged into a batch if:
 - * The availability of any non-singleton service, running on this node, does not go below the specified service availability factor (or the default of 50%).
 - * There is a singleton service running on this node and the batch does not contain any of the relocation target nodes for the service.
- Restarts the Oracle Grid Infrastructure stack batch by batch.
- Service availability factor (`-saf Z+`): You can specify a positive number, as a percentage, that will indicate the minimum number of database instances on which a database service must be running. For example:
 - If you specify `-saf 50` for a service running on two instances, then only one instance can go offline at a time.
 - If you specify `-saf 50` for a service running on three instances, then only one instance can go offline at a time.
 - If you specify `-saf 75` for a service running on two instances, then an error occurs because the target can never be met.
 - The service availability factor is applicable for services running on at least two instances. As such, the service availability factor can be 0% to indicate a non-rolling move, but not 100%. The default is 50%.
 - If you specify a service availability factor for singleton services, then the parameter will be ignored because the availability of such services is 100% and the services will be relocated.
- `-eval`: You can optionally use this parameter to view the auto-generated batches. This parameter also shows the sequence of the move operation without actually patching the software.

Patching Oracle Database Using Batches

During database patching, Fleet Patching and Provisioning can sequentially process batches of nodes, with a number of nodes in each batch being restarted in parallel. This method maximizes service availability during the patching process. You can define the batches on the command line or choose to have Fleet Patching and Provisioning generate the list of batches based on its analysis of the database services running in the cluster.

Adaptive Oracle RAC-Rolling Patching for OJVM Deployments

In a clustered environment, the default approach for applying database maintenance with Fleet Patching and Provisioning is Oracle RAC rolling. However, non-rolling may

be required if the new (patched) database home contains OJVM patches. In this case, Fleet Patching and Provisioning determines whether the rolling approach is possible, and rolls when applicable. (See MOS Note 2217053.1 for details.)

Related Topics

- [rhpctl move gihome](#)
Moves the Oracle Grid Infrastructure software stack from one home to another.

Oracle Grid Infrastructure Management

The Oracle Fleet Patching and Provisioning Server provides an efficient and secure platform for the distribution of Oracle Grid Infrastructure homes to targets and Oracle Fleet Patching and Provisioning Clients.

Also, Oracle Fleet Patching and Provisioning Clients have the ability to fetch Oracle Grid Infrastructure homes from the Oracle Fleet Patching and Provisioning Server.

Oracle Grid Infrastructure homes are distributed in the form of working copies of gold images. After a working copy has been provisioned, Oracle Fleet Patching and Provisioning can optionally configure Oracle Grid Infrastructure. This gives Oracle Fleet Patching and Provisioning the ability to create an Oracle Grid Infrastructure installation on a group of one or more nodes that initially do not have Oracle Grid Infrastructure installed.

Oracle Fleet Patching and Provisioning also has commands for managing Oracle Grid Infrastructure homes, such as switching to a patched home or upgrading to a new Oracle Grid Infrastructure version. These are both single commands that orchestrate the numerous steps involved. Reverting to the original home is just as simple. Also, Oracle Fleet Patching and Provisioning can add or delete nodes from an Oracle Grid Infrastructure configuration.

This section discusses the following topics:

- [About Deploying Oracle Grid Infrastructure Using Oracle Fleet Patching and Provisioning](#)
- [Provisioning Oracle Grid Infrastructure Software](#)
- [Patching Oracle Grid Infrastructure Software](#)
- [Oracle Fleet Patching and Provisioning Self Upgrade](#)
- [Patching Oracle Grid Infrastructure Using Local-Mode Configuration](#)
- [Error Prevention and Automated Recovery Options](#)
- [Upgrading Oracle Grid Infrastructure Software](#)
- [Oracle Fleet Patching and Provisioning Automation for GIMR Integration](#)

About Deploying Oracle Grid Infrastructure Using Oracle Fleet Patching and Provisioning

You can use Oracle Fleet Patching and Provisioning to provision and maintain your Oracle Grid Infrastructure homes.

Oracle Fleet Patching and Provisioning enables mass deployment and maintenance of standard operating environments for databases, clusters, and user-defined software types.

Oracle FPP enables you to install clusters, and provision, patch, scale, and upgrade Oracle Grid Infrastructure, Oracle Restart, and Oracle Database homes. The supported releases are 11.2, 12.1, 12.2, 18c, and later releases. You can also provision applications and middleware using Oracle Fleet Patching and Provisioning.

Oracle Fleet Patching and Provisioning is a service in Oracle Grid Infrastructure that you can use in either of the following modes:

- Central Oracle Fleet Patching and Provisioning Server

The Oracle Fleet Patching and Provisioning Server stores and manages standardized images, called gold images. Gold images can be deployed to any number of nodes across the data center. You can create new clusters and databases on the deployed homes and can use them to patch, upgrade, and scale existing installations.

The Oracle Fleet Patching and Provisioning Server can manage the following types of installations:

- Software homes on the cluster hosting the Oracle Fleet Patching and Provisioning Server itself.
- Installations running Oracle Grid Infrastructure 11g Release 2 (11.2) and 12c Release 1 (12.1).
- Oracle Fleet Patching and Provisioning Clients running Oracle Grid Infrastructure 12c Release 2 (12.2) and later releases.
- Installations running without Oracle Grid Infrastructure.

The Oracle Fleet Patching and Provisioning Server can provision new installations, and manage existing installations, without requiring any changes to the existing installations. The Oracle Fleet Patching and Provisioning Server can automatically share gold images among peer servers to support enterprises with geographically distributed data centers.

- Oracle Fleet Patching and Provisioning Client

The Oracle Fleet Patching and Provisioning Client can be managed from the Oracle Fleet Patching and Provisioning Server, or directly by executing commands on the client itself. The Oracle Fleet Patching and Provisioning Client is a service built into the Oracle Grid Infrastructure and is available in Oracle Grid Infrastructure 12c Release 2 (12.2) and later releases. The Oracle Fleet Patching and Provisioning Client can retrieve gold images from the Oracle Fleet Patching and Provisioning Server, upload new images based on the policy, and apply maintenance operations to itself.

Provisioning Oracle Grid Infrastructure Software

Fleet Patching and Provisioning has several methods to provision and, optionally, configure Oracle Grid Infrastructure and Oracle Restart grid infrastructure homes.

Fleet Patching and Provisioning can provision and configure Oracle Grid Infrastructure on one or more nodes that do not currently have a Grid home, and then configure Oracle Grid Infrastructure to form a single-node or multi-node Oracle Grid Infrastructure installation.

Use the `rhptl add workingcopy` command to install and configure Oracle Grid Infrastructure, and to enable simple and repeatable creation of standardized deployments.

The Fleet Patching and Provisioning Server can also provision an Oracle Grid Infrastructure home to a node or cluster that is currently running Oracle Grid Infrastructure. The currently running Grid home can be a home that Fleet Patching and Provisioning did not provision (an *unmanaged* home) or a home that Fleet Patching and Provisioning did provision (a *managed* home).


You can also provision an Oracle Restart grid infrastructure to a node in the cluster.

In either case, use the `-softwareonly` parameter of the `rhptl add workingcopy` command. This provisions but does not activate the new Grid home, so that when you are ready to switch to that new home, you can do so with a single command.

- To inform Fleet Patching and Provisioning the nodes on which to install Oracle Grid Infrastructure, and to configure Oracle Grid Infrastructure, you provide directions in a response file, as in the following example:

```
$ rhptl add workingcopy -workingcopy GI_HOME_11204_WCPY -image  
GI_HOME_11204 -responsefile /u01/app/rhpinfo/GI_11204_install.txt  
{authentication_option}
```

The preceding command provisions the `GI_HOME_11204_WCPY` working copy based on the `GI_HOME_11204` gold image to a target specified in the `GI_11204_install.txt` response file. In addition to identifying the target nodes, the response file specifies information about the Oracle Grid Infrastructure configuration, such as Oracle ASM and GNS parameters.

 **Note:**

The `oracle.install.crs.rootconfig.executeRootScript=xxx` response file parameter is overridden and always set to `false` for Fleet Patching and Provisioning, regardless of what you specify in the response file.

- To provision an Oracle Grid Infrastructure home to a node or cluster that is currently running Oracle Grid Infrastructure:

```
$ rhptl add workingcopy -workingcopy GI_HOME_12201_PATCHED_WCPY -  
image GI_HOME_12201_PSU1 -client CLUST_002 -softwareonly
```

The preceding command provisions a new working copy based on the `GI_HOME_12201_PSU1` gold image to the Fleet Patching and Provisioning Client (that is running Oracle Grid Infrastructure 12c release 2 (12.2)) named `CLUST_002`. When you provision to a target that is not running Oracle Grid Infrastructure 12c release 2 (12.2) (such as, a target running Oracle Grid Infrastructure 12c release 1 (12.1) or Oracle Grid Infrastructure 11g release 2 (11.2)), use the `-targetnode` parameter instead of `-client`.

- Specify a target node on which you want to provision an Oracle Restart grid infrastructure, as follows:

```
$ rhpctl add workingcopy -workingcopy SIHA_GI -  
image goldimage -targetnode remote_node_name -responsefile  
Oracle_Restart_response_file {authentication_option}
```

Related Topics

- [Authentication Options for Oracle Fleet Patching and Provisioning Operations](#)
Some RHPCTL commands show authentication choices as an optional parameter.

Patching Oracle Grid Infrastructure Software

Fleet Patching and Provisioning provides three methods to patch Oracle Grid Infrastructure software homes: rolling, non-rolling, and in batches.

Patching Oracle Grid Infrastructure software involves moving the Grid home to a patched version of the current Grid home. When the patching operation is initiated by a Fleet Patching and Provisioning Server or Client, the patched version must be a working copy of a gold image. The working copy to which you are moving the Grid home can be at a lower patch level than the current home. This facilitates rollback if any problems occur after moving to the higher-level patched home.

You can also perform this operation using the independent automaton in an environment where no Fleet Patching and Provisioning Server is present. In this case, the source and destination homes are not working copies of gold images, but are two installed homes that you deployed with some method other than using Fleet Patching and Provisioning.

For information about patching using batches, refer to [Patching Oracle Grid Infrastructure and Oracle Database Using Batches](#).

This section includes the following topics:

- [Patching Oracle Grid Infrastructure Using the Rolling Method](#)
- [Patching Oracle Grid Infrastructure Using the Non-Rolling Method](#)
- [Combined Oracle Grid Infrastructure and Oracle Database Patching](#)

Related Topics

- [rhpctl add workingcopy](#)
- [rhpctl move gihome](#)

Patching Oracle Grid Infrastructure Using the Rolling Method

The rolling method for patching Oracle Grid Infrastructure is the default method.

You use the `rhpctl move gihome` command (an atomic operation), which returns after the Oracle Grid Infrastructure stack on each node has been restarted on the new home. Nodes are restarted sequentially, so that only one node at a time will be offline, while all other nodes in the cluster remain online.

- Move the Oracle Grid Infrastructure home to a working copy of the same release level, as follows:

```
$ rhpctl move gihome -client cluster_name -sourcewc Grid_home_1 -  
destwc Grid_home_2
```

The preceding command moves the running Oracle Grid Infrastructure home from the current managed home (the `sourcewc`) to the patched home (`destwc`) on the specific client cluster. The patched home must be provisioned on the client.

- If the move operation fails at some point before completing, then you can rerun the operation by running the command again and the operation will resume where it left off. This enables you to fix whatever problem caused the failure and resume processing from the point of failure. Or you can undo the partially completed operation and return the configuration to its initial state, as follows:

```
$ rhpctl move gihome -destwc destination_workingcopy_name -revert  
[authentication_option]
```

You can use the `-revert` parameter with an un-managed home.

Notes:

- You cannot move the Grid home to a home that Fleet Patching and Provisioning does not manage. Therefore, rollback (to the original home) applies only to moves between two working copies. This restriction does not apply when using the independent automaton since it operates on unmanaged homes only.
- You can delete the source working copy at any time after moving a Grid home. Once you delete the working copy, however, you cannot perform a rollback. Also, use the `rhpctl delete workingcopy` command (as opposed to `rm`, for example) to remove the source working copy to keep the Fleet Patching and Provisioning inventory correct.
- If you use the `-abort` parameter to terminate the patching operation, then Fleet Patching and Provisioning does not clean up or undo any of the patching steps. The cluster, databases, or both may be in an inconsistent state because all nodes are not patched.

Patching Oracle Grid Infrastructure Using the Non-Rolling Method

You can use the `-nonrolling` parameter with the `rhpctl move gihome` command, which restarts the Oracle Grid Infrastructure stack on all nodes in parallel.

As with the rolling method, this is an atomic command which returns after all nodes are online.

- Use the following command to patch Oracle Grid Infrastructure in a non-rolling fashion:

```
$ rhpctl move gihome -client cluster_name -sourcewc Grid_home_1 -
destwc Grid_home_2 -nonrolling
```

Combined Oracle Grid Infrastructure and Oracle Database Patching

When you patch an Oracle Grid Infrastructure deployment, Fleet Patching and Provisioning enables you to simultaneously patch the Oracle Database homes on the cluster, so you can patch both types of software homes in a single maintenance operation.

Note:

You cannot patch both Oracle Grid Infrastructure and Oracle Database in combination, with the independent automaton.

The following optional parameters of the `rhpctl move gihome` command are relevant to the combined Oracle Grid Infrastructure and Oracle Database patching use case:

- `-auto`: Automatically patch databases along with patching Oracle Grid Infrastructure
- `-dbhomes mapping_of_Oracle_homes`: Mapping of source and destination working copies in the following format:

```
sourcewc1=destwc1,...,source_oracle_home_path=destwcN
```

- `-dblist db_name_list`: Patch only the specified databases
- `-excludedblist db_name_list`: Patch all databases except the specified databases
- `-nodatapatch`: Indicates that `datapatch` is not to be run for databases being moved

As an example, assume that a Fleet Patching and Provisioning Server with Oracle Grid Infrastructure 12c release 2 (12.2) has provisioned the following working copies on an Oracle Grid Infrastructure 12c release 1 (12.1.0.2) target cluster which includes the node `test_749`:

- `GI121WC1`: The active Grid home on the Oracle Grid Infrastructure 12c release 1 (12.1.0.2) cluster
- `GI121WC2`: A software-only Grid home on the Oracle Grid Infrastructure 12c release 1 (12.1.0.2) cluster
- `DB121WC1`: An Oracle RAC 12c release 1 (12.1.0.2.0) database home running database instances
- `DB121025WC1`: An Oracle RAC 12c release 1 (12.1.0.2.5) database home with no database instances (this is the patched home)
- `DB112WC1`: An Oracle RAC 11g release 2 (11.2.0.4.0) database home running database instances

- DB112045WC1: An Oracle RAC 11g release 2 (11.2.0.4.5) database home with no database instances (this is the patched home)

Further assume that you want to simultaneously move

- Oracle Grid Infrastructure from working copy GI121WC1 to working copy GI121WC2
- Oracle RAC Database db1 from working copy DB121WC1 to working copy DB121025WC1
- Oracle RAC Database db2 in working copy DB112WC1 to working copy DB112045WC1

The following single command accomplishes the moves:

```
$ rhpctl move gihome -sourcewc GI121WC1 -destwc GI121WC2 -auto  
-dbhomes DB121WC1=DB121025WC1,DB112WC1=DB112045WC1 -targetnode  
test_749 {authentication_option}
```

Notes:

- If you have an existing Oracle home that is not currently a working copy, then specify the Oracle home path instead of the working copy name for the source home. In the preceding example, if the Oracle home path for an existing 12.1.0.2 home is `/u01/app/prod/12.1.0.2/dbhome1`, then replace `DB121WC1=DB121025WC1` with `/u01/app/prod/12.1.0.2/dbhome1=DB121025WC1`.
- If the move operation fails at some point before completing, then you can either resolve the cause of the failure and resume the operation by rerunning the command, or you can undo the partially completed operation by issuing the following command, which restores the configuration to its initial state:

```
$ rhpctl move gihome -destwc GI121WC2 -revert  
{authentication_option}
```

In the preceding command example, the Oracle Grid Infrastructure 12c release 1 (12.1.0.2) Grid home moves from working copy GI121WC1 to working copy GI121WC2, databases running on working copy DB121WC1 move to working copy DB121025WC1, and databases running on working copy DB112WC1 move to working copy DB112045WC1.

For each node in the client cluster, RHPCTL:

1. Runs any configured pre-operation user actions for moving the Oracle Grid Infrastructure (`move gihome`).
2. Runs any configured pre-operation user actions for moving the database working copies (`move database`).
3. Stops services running on the node, and applies drain and disconnect options.
4. Performs the relevant patching operations for Oracle Clusterware and Oracle Database.
5. Runs any configured post-operation user actions for moving the database working copies (`move database`).

6. Runs any configured post-operation user actions for moving the Oracle Grid Infrastructure working copy (`move gihome`).

Related Topics

- [rhpctl move gihome](#)
Moves the Oracle Grid Infrastructure software stack from one home to another.

Zero-Downtime Oracle Grid Infrastructure Patching

Use Fleet Patching and Provisioning to patch Oracle Grid Infrastructure without bringing down Oracle RAC database instances.

Current methods of patching the Oracle Grid Infrastructure require that you bring down all Oracle RAC database instances on the node where you are patching the Oracle Grid Infrastructure home. This issue is addressed in the Grid Infrastructure layer where by the database instances can continue to run during the grid infrastructure patching.

To enable zero-downtime Oracle Grid Infrastructure patching, use the `rhpctl move gihome` command in a manner similar to the following:

```
rhpctl move gihome -tgip
```

Patching System Software Binaries

When using Zero Downtime Patching, only the binaries in the Oracle Grid Infrastructure user space are patched. Additional Oracle Grid Infrastructure OS system software, kernel modules and system commands including `ACFS`, `AFD`, `OLFS`, and `OKA`, are not updated. These commands continue to run the version previous to the patch version. After patching, the OPatch inventory displays the new patch number in the inventory; however, the running OS system software does not contain these changes. Only the OS system software that is available in the Grid Infrastructure home has been patched.

To determine the OS system software that is available in the Grid Infrastructure home, you can run the `crsctl query driver activeversion -all` command. To determine what OS system software is running on the system, use `crsctl query driver softwareversion -all`.

To update the Grid Infrastructure OS system software on a single node, you must completely stop the Grid Infrastructure software. To stop the Grid Infrastructure software, you must stop the Oracle RAC databases on the single node. After stopping the Oracle RAC databases, run `root.sh -updateosfiles` to update all the Grid Infrastructure OS system software on the single node.

See Also:

- *Oracle Automatic Storage Management Cluster File System Administrator's Guide* for information about Oracle Patching and Oracle ACFS

Patching Oracle Grid Infrastructure Using Local-Mode Configuration

When you install Oracle Grid Infrastructure or when you upgrade an older version to this current version, the Fleet Patching and Provisioning Server is configured automatically in local mode.

The local-mode operation enables you to perform grid infrastructure and database patching operations on the local cluster in a simplified environment without having to register or deploy gold images. Deploy either the grid infrastructure or the database patched home and run the patch operation using either the `rhpcctl move gihome` or `rhpcctl move database` command, specifying the source and destination paths instead of working copy names.

Note:

Fleet Patching and Provisioning Server 21c is started automatically when patching command is invoked and the dependent resources are set up during the automatic startup process.

To switch the Fleet Patching and Provisioning Server from local mode to the regular, central mode (to manage remote targets), you must delete the current Fleet Patching and Provisioning Server in local mode, as follows:

```
$ srvctl stop rhpsserver
$ srvctl remove rhpsserver
```

Proceed with the steps described in "Creating a Fleet Patching and Provisioning Server" to create the central-mode Fleet Patching and Provisioning Server.

- The independent automaton for patching Oracle Grid Infrastructure performs all of the steps necessary to switch from one home to another. Because the automaton is not aware of gold images, moving the database requires two home paths, as follows:

```
$ rhpcctl move gihome -desthome destination_oracle_home_path -
sourcehome Oracle_home_path
```

Use the following `rhpcctl move gihome` command parameters for the patching operation:

- `-node`: If the home you are moving is an Oracle Grid Infrastructure home installed on more than one node, then the default operation is a rolling update on all nodes. To apply a patch to just one node, specify the name of that node with this parameter.
- `-nonrolling`: If the home you are moving is an Oracle Grid Infrastructure home installed on more than one node, then the default operation is a rolling update on all nodes. To patch all nodes in a nonrolling manner, use this parameter instead of the `-node` parameter.
- `-ignorewcpatches`: By default, Fleet Patching and Provisioning will not perform the move operation if the destination home is missing any patches present in

the source home. You can override this functionality by using this parameter, for example, to move back to a previous source home if you must undo an update.

Related Topics

- [Creating a Fleet Patching and Provisioning Server](#)
The Fleet Patching and Provisioning Server uses a repository that you create in an Oracle ACFS file system in which you store all the software homes that you want to make available to clients and targets.

Error Prevention and Automated Recovery Options

Fleet Patching and Provisioning has error prevention and automated recovery options to assist you during maintenance operations.

During maintenance operations, errors must be avoided whenever possible and, when they occur, you must have automated recovery paths to avoid service disruption.

Error Prevention

Many RHPCTL commands include the `-eval` parameter, which you can use to run the command and evaluate the current configuration without making any changes to determine if the command can be successfully run and how running the command will impact the configuration. Commands that you run using the `-eval` parameter run as many prerequisite checks as possible without changing the configuration. If errors are encountered, then RHPCTL reports them in the command output. After you correct any errors, you can run the command again using `-eval` to validate the corrections. Running the command successfully using `-eval` provides a high degree of confidence that running the actual command will succeed.

You can test commands with the `-eval` parameter outside of any maintenance window, so the full window is available for the maintenance procedure, itself.

Automated Recovery Options

During maintenance operations, errors can occur either in-flight (for example, partway through either an `rhpcctl move database` or `rhpcctl move gihome` command) or after a successful operation (for example, after an `rhpcctl move database` command, you encounter performance or behavior issues).

In-Flight Errors

Should in-flight errors occur during move operations:

- Correct any errors that RHPCTL reports and rerun the command, which will resume running at the point of failure.
If rerunning the command succeeds and the move operation has a post-operation user action associated with it, then the user action is run. If there is a pre-operation user action, however, then RHPCTL does not rerun the command.
- Run a new move command, specifying only the destination from the failed move (working copy or unmanaged home), an authentication option, if required, and use the `-revert` parameter. This will restore the configuration to its initial state.
No user actions associated with the operation are run.
- Run a new move command, specifying only the destination from the failed move (working copy or unmanaged home), an authentication option if required, and

the `-abort` parameter. This leaves the configuration in its current state. Manual intervention is required at this point to place the configuration in a final state.

No user actions associated with the operation are run.

Post-Update Issues

Even after a successful move operation to a new database or Oracle Grid Infrastructure home, you still may need to undo the change and roll back to the prior home. You can do this by rerunning the command with the source and destination homes reversed. This is, effectively, a fresh move operation performed without reference to the previous move operation.

Note:

For the independent automatons, the source and destination homes are always unmanaged homes (those homes not provisioned by Fleet Patching and Provisioning). When the move operation is run on a Fleet Patching and Provisioning Server or Fleet Patching and Provisioning Client, the destination home must be a managed home that was provisioned by Fleet Patching and Provisioning.

Upgrading Oracle Grid Infrastructure Software

If you are using Fleet Patching and Provisioning, then you can use a single command to upgrade an Oracle Grid Infrastructure home.

Fleet Patching and Provisioning supports upgrades to Oracle Grid Infrastructure 21c from 19c, 18c, 12.2, 12.1, and 11.2. The destination for the upgrade can be a working copy of a gold image already provisioned or you can choose to create the working copy as part of this operation.

As an example, assume that a target cluster is running Oracle Grid Infrastructure on an Oracle Grid Infrastructure home that was provisioned by Fleet Patching and Provisioning. This Oracle Grid Infrastructure home is 19c and the working copy is named accordingly, for example `GIOH19C`.

After provisioning a working copy version of Oracle Grid Infrastructure 21c (named `GIOH21C` in this example) and GIMR (named `GIMROH21c` in this example), you can upgrade to that working copy with this single command:

```
$ rhpctl upgrade gihome -sourcewc GIOH19C -destwc GIOH21C -gimrwc  
GIMROH21c
```

If the cluster that you are upgrading has a local GIMR, then follow the steps in the *Provisioning an Oracle Grid infrastructure 21c with GIMR configured* section.

Fleet Patching and Provisioning is able to identify the cluster to upgrade based on the name of the source working copy. If the target cluster was running on an unmanaged Oracle Grid Infrastructure home, then you would specify the path of the source home rather than providing a source working copy name, and you must also specify the target cluster.

 **Note:**

You can delete the source working copy at any time after completing an upgrade. Once you delete the working copy, however, you cannot perform a rollback. Also, use the `rhpctl delete workingcopy` command (as opposed to `rm`, for example) to remove the source working copy to keep the Fleet Patching and Provisioning inventory correct.

Related Topics

- [Oracle Fleet Patching and Provisioning Automation for GIMR Integration](#)

Oracle Fleet Patching and Provisioning Self Upgrade

Perform these steps when upgrading Oracle Grid Infrastructure from 19c to 21c using the Oracle Fleet Patching and Provisioning (Oracle FPP) self upgrade feature.

1. Add a GIMR working copy of Oracle Database 21c on the Fleet Patching and Provisioning Server 19c with the `-readonly` and `-ignoreprereq` options.

```
$ rhpctl add workingcopy -workingcopy GIMR_working_copy_name -path  
path_to_software_home  
-oraclebase Oracle_base_path -storagetype LOCAL -image image_name  
-readonly -ignoreprereq
```

2. Add software only Oracle Grid Infrastructure 21c working copy on the Fleet Patching and Provisioning Server 19c.

```
$ rhpctl add workingcopy -workingcopy GI_working_copy_name -path  
path_to_software_21c_home  
[-oraclebase Oracle_base_path] -softwareonly -image  
21c_GI_image_name
```

3. Unset the `ORACLE_HOME` environment variable.

```
$ unset ORACLE_HOME
```

4. Run the `upgrade gihome` command from the software only Oracle Grid Infrastructure 21c working copy using the `rhpctl.sh` script.

```
$ ./rhpctl.sh upgrade gihome -sourcehome 19c_GI_home -destwc  
GI_21c_working_copy_name  
-gimrwc GIMR_working_copy_name -batches "(batch1),(batch2)"
```

Related Topics

- [Upgrading Oracle Grid Infrastructure Software](#)
If you are using Fleet Patching and Provisioning, then you can use a single command to upgrade an Oracle Grid Infrastructure home.

Starting Oracle FPP Server After Manually Upgrading Oracle Grid Infrastructure

If you upgrade Oracle Grid Infrastructure manually, without using Oracle Fleet Patching and Provisioning (Oracle FPP) self upgrade feature, then Oracle FPP Server does not start after the upgrade.

When you manually upgrade Oracle Grid Infrastructure, the file system resources are disabled and that does not allow the Oracle FPP Server to start. When file system resources are disabled, you may get an error while starting the Oracle FPP Server. To resolve this error, you must first enable the file system and then start the Oracle FPP server.

1. Enable file system on all the volumes and the storage disk groups.

```
./srvctl enable filesystem -volume volume_name -diskgroup diskgroup_name
```

2. Enable the volume and the disk group on which you enabled the file system.

```
./srvctl enable volume -volume volume_name -diskgroup diskgroup_name
```

3. Start the Oracle FPP Server.

```
./srvctl start rhpserver
```

Oracle Fleet Patching and Provisioning Automation for GIMR Integration

Oracle Fleet Patching and Provisioning automation for Grid Infrastructure Management Repository (GIMR) integration can be performed on Oracle Grid infrastructure for the following operations:

- Provisioning an Oracle Grid infrastructure 21c with GIMR configured
- Upgrading to 21c an Oracle Grid infrastructure that has GIMR configured

Provisioning an Oracle Grid infrastructure 21c with GIMR configured

1. Import the Oracle Grid Infrastructure image with the `rhpcctl import image` command.
2. Import the Oracle Database image with the `rhpcctl import image` command.
3. Add the Oracle Grid Infrastructure working copy with the `rhpcctl add workingcopy` command.

Specify the use of a local GIMR in the response file using the following settings.

- `oracle.install.crs.configureGIMR=true`
- `oracle.install.crs.configureRemoteGIMR=false`
- `oracle.install.crs.RemoteGIMRCredFile=`

4. Add the Oracle Database working copy with the `rhpcctl add workingcopy` command. The owner of the database working copy must be the same as the owner of the Oracle Grid Infrastructure working copy.

This use of the `rhpcctl add workingcopy` command is only used by GIMR, and cannot be used to provision customer databases.

5. Add the GIMR database to the database working copy with the `rhpcctl add database` command using the `-gimr` flag.

Upgrading to 21c an Oracle Grid infrastructure that has GIMR configured

1. Import the Oracle Grid Infrastructure image of the version that you want to upgrade to 21c with the `rhpcctl import image` command.
2. Import the Oracle Database image of the version that you want to upgrade to 21c with the `rhpcctl import image` command.
3. Add a software only Oracle Grid Infrastructure working copy with the `rhpcctl add workingcopy` command using the `-softwareonly` flag.
4. Add the database working copy for the GIMR upgrade with the `rhpcctl add workingcopy` command using the `-gimr` flag. The owner of the database working copy must be the same as the owner of the Oracle Grid Infrastructure working copy.

This use of the `rhpcctl add workingcopy` command is only used by GIMR, and cannot be used to provision customer databases.

5. Upgrade both the Oracle Grid Infrastructure and GIMR homes with a single `rhpcctl upgrade gihome` command using the `-gimrwc gimr_wc` option, where *gimr_wc* specifies the working copy created in the previous step (**step 4**).

Oracle Database Software Management

The Oracle Fleet Patching and Provisioning Server provides an efficient and secure platform for the distribution of Oracle Database Homes to targets and Oracle Fleet Patching and Provisioning Clients.

Also, Oracle Fleet Patching and Provisioning Clients have the ability to fetch database homes from the Oracle Fleet Patching and Provisioning Server.

Oracle Database homes are distributed in the form of working copies of gold images. Database instances (one or more) can then be created on the working copy.

Oracle Fleet Patching and Provisioning also has commands for managing existing databases, such as switching to a patched home or upgrading to a new database version. These are both single commands which orchestrate the numerous steps involved. Reverting to the original home is just as simple.

This section contains the following topics:

- [Provisioning a Copy of a Gold Image of a Database Home](#)
- [Creating an Oracle Database on a Copy of a Gold Image](#)
- [Patching Oracle Database Software](#)
- [Patching Oracle Database with the Independent Automaton](#)
- [Upgrading Oracle Database Software](#)

Provisioning a Copy of a Gold Image of a Database Home

Use the `rhptl add workingcopy` command to provision a working copy of a database home on a Fleet Patching and Provisioning Server, Client, or target.

- Run the `rhptl add workingcopy` command on a Fleet Patching and Provisioning Server, similar to the following example:

```
$ rhptl add workingcopy -image db12c -path /u01/app/dbusr/product/  
12.2.0/db12201  
-client client_007 -oraclebase /u01/app/dbusr/ -workingcopy  
wc_db122_1
```

The preceding command example creates a working copy named `wc_db122_1` on all nodes of the Fleet Patching and Provisioning Client cluster named `client_007`. The gold image `db12c` is the source of the workingcopy. The directory path locations that you specify in the command must be empty.

Related Topics

- [rhptl add workingcopy](#)

Creating an Oracle Database on a Copy of a Gold Image

Create an Oracle Database on a working copy.

The Fleet Patching and Provisioning Server can add a database on a working copy that is on the Fleet Patching and Provisioning Server, itself, a Fleet Patching and Provisioning Client, or a non-Fleet Patching and Provisioning Client target. A Fleet Patching and Provisioning Client can create a database on a working copy that is running on the Fleet Patching and Provisioning Client, itself.

- After you create a working copy of a gold image and provision that working copy to a target, you can create an Oracle Database on the working copy using the `rhptl add database` command, similar to the following command example, which creates an Oracle Real Application Clusters (Oracle RAC) database called `db12201` on a working copy called `wc_db122_1`:

```
$ rhptl add database -workingcopy wc_db122_1 -dbname db12201 -node  
client_007_node1,client_007_node2 -dbtype RAC -datafileDestination  
DATA007_DG
```

The preceding example creates an administrator-managed Oracle RAC database on two nodes in a client cluster. The data file destination is an Oracle ASM disk group that was created prior to running the command. Additionally, you can create Oracle RAC One Node and non-cluster databases.

 **Note:**

When you create a database using Fleet Patching and Provisioning, the feature uses random passwords for both the SYS and SYSTEM schemas in the database and you cannot retrieve these passwords. A user with the DBA or operator role must connect to the database, locally, on the node where it is running and reset the passwords to these two accounts.

Patching Oracle Database Software

To patch an Oracle database, you move the database home to a new home, which includes the patches you want to implement.

Use the `rhpcctl move database` command to move one or more database homes to a working copy of the same database release level. The databases may be running on a working copy, or on an Oracle Database home that is not managed by Fleet Patching and Provisioning.

When the move operation is initiated by a Fleet Patching and Provisioning Server or Client, the version moved to must be a working copy of a gold image. You can also perform this operation using the independent automaton in an environment where no Fleet Patching and Provisioning Server is present. In this case, the source and destination homes are not working copies of gold images, but are two installed homes that you deployed with some method other than using Fleet Patching and Provisioning.

The working copy to which you are moving the database can be at a lower patch level than the current database home. This facilitates rollback in the event that you encounter any problems after moving to the higher level patched home.

The working copy to which you are moving the database home can be at the same patch level as the original working copy. This is useful if you are moving a database home from one storage location to another, or if you wish to convert an unmanaged home to a managed home while staying at the same patch level.

Fleet Patching and Provisioning applies all patches out-of-place, minimizing the downtime necessary for maintenance. Fleet Patching and Provisioning also preserves the current configuration, enabling the rollback capability previously described. By default, Fleet Patching and Provisioning applies patches in a rolling manner, which reduces, and in many cases eliminates, service downtime. Use the `-nonrolling` option to perform patching in non-rolling mode. The database is then completely stopped on the old `ORACLE_HOME`, and then restarted to make it run from the newly patched `ORACLE_HOME`.

For information about patching using batches, refer to [Patching Oracle Grid Infrastructure and Oracle Database Using Batches](#).

 **Note:**

Part of the patching process includes applying Datapatch. When you move an Oracle Database 12c release 1 (12.1) or higher, Fleet Patching and Provisioning completes this step for you. When you move to a version previous to Oracle Database 12c release 1 (12.1), however, you must run Datapatch manually. Fleet Patching and Provisioning is Oracle Data Guard-aware, and will not apply Datapatch to Oracle Data Guard standbys.

Workflow for Database Patching

Assume that a database named `myorcldb` is running on a working copy that was created from an Oracle Database 12c release 2 (12.2) gold image named `DB122`. The typical workflow for patching an Oracle Database home is as follows:

1. Create a working copy of the Oracle Database that you want to patch, in this case `DB122`.
2. Apply the patch to the working copy you created.
3. Test and validate the patched working copy.
4. Use the `rhptcl add image` command to create a gold image (for example, `DB122_PATCH`) from the patched working copy.

 **Note:**

The working copy you specify in the preceding command must be hosted on the Fleet Patching and Provisioning Server in Fleet Patching and Provisioning-managed storage.

5. Delete the patched working copy with the patched Oracle Database using the `rhptcl delete workingcopy` command.

 **Note:**

Do not remove directly using the `rm` command or some other method, because this does not update the Fleet Patching and Provisioning inventory information.

6. Create a working copy from the patched gold image, (`DB122_PATCH`).
7. Move `myorcldb` to the working copy you just created.
8. When you are confident that you will not need to roll back to the working copy on which the database was running at the beginning of the procedure, delete that working copy using the `rhptcl delete workingcopy` command.

Related Topics

- [Patching Oracle Grid Infrastructure Software](#)
- [Provisioning Copies of Gold Images](#)
- [Adding Gold Images to the Fleet Patching and Provisioning Server](#)

- [RHPCTL Command Reference](#)

Patching Oracle Database with the Independent Automaton

The independent local-mode automaton updates Oracle Database homes, including Oracle Database single-instance databases in a cluster or standalone (with no Oracle Grid Infrastructure), an Oracle RAC database, or an Oracle RAC One Node database.

In a clustered environment, the database source home can be Oracle Database 11g (11.2.0.4), 12c (12.1.0.2), 12c (12.2.0.1), or later.

In a standalone (non-clustered) environment, the database home must be Oracle Database 18c or later.

The automaton runs locally on the deployment and does not require an Oracle Fleet Patching and Provisioning Server in the architecture. (If there is an Oracle Fleet Patching and Provisioning Server in the architecture, then the automaton does not communicate with it, and the Fleet Patching and Provisioning Server cannot interact with the independent automaton.)

- The independent automaton for Oracle Database patching performs all of the steps necessary to switch from one home to another. Because the automaton is not aware of gold images, moving the database requires two home paths, as follows:

```
$ rhpctl move database -sourcehome Oracle_home_path -desthome  
destination_oracle_home_path
```

Use the following `rhpctl move database` command parameters for any of the patching scenarios:

- `-dbname`: If the database home is hosting more than one database, you can move specific databases by specifying a comma-delimited list with this parameter. Databases not specified are not moved. If you do not use this parameter, then RHPCTL moves all databases.

 **Note:**

If you are moving a non-clustered (single-instance) database, then, for the value of the `-dbname` parameter, you must specify the SID of the database instead of the database name.

- `-ignorewcpatches`: By default, Oracle Fleet Patching and Provisioning will not perform the move operation if the destination home is missing any patches present in the source home. You can override this functionality by using this parameter, for example, to move back to a previous source home if you must undo an update.

The following parameters apply only to clustered environments:

- `-node`: If the home you are moving is a database home installed on more than one node, then the default operation is a rolling update on all nodes. To apply a patch to just one node, specify the name of that node with this parameter.
- `-nonrolling`: If the home you are moving is a database home installed on more than one node, then the default operation is a rolling update on all nodes. To patch all nodes in a nonrolling manner, use this parameter instead of the `-node` parameter.

- `-disconnect` and `-noreplay`: Applies to single-instance Oracle Databases, and Oracle RAC, and Oracle RAC One Node database. Use the `-disconnect` parameter to disconnect all sessions before stopping or relocating services. If you choose to use `-disconnect`, then you can choose to use the `-noreplay` parameter to disable session replay during disconnection.

`-drain_timeout`: Applies to single-instance Oracle Databases, Oracle RAC, and Oracle RAC One Node database. Use this parameter to specify the time, in seconds, allowed for session draining to be completed from each node. Accepted values are an empty string (""), 0, or any positive integer. The default value is an empty string, which means that this parameter is not set. This is applicable to older versions to maintain traditional behavior. If it is set to 0, then the stop option is applied immediately.

The draining period is intended for planned maintenance operations. During the draining period, on each node in succession, all current client requests are processed, but new requests are not accepted.

`-stopoption`: Applies to single-instance Oracle Databases, Oracle RAC, and Oracle RAC One Node database. Specify a stop option for the database. Stop options include: ABORT, IMMEDIATE, NORMAL, TRANSACTIONAL, and TRANSACTIONAL_LOCAL.

 **Note:**

The `rhptcl move database` command is Oracle Data Guard-aware, and will not run Datapatch if the database is an Oracle Data Guard standby.

Related Topics

- [rhptcl move database](#)
Moves one or more databases from a source working copy or any Oracle Database home to a patched working copy.

Upgrading Oracle Database Software

Fleet Patching and Provisioning provides two options for upgrading Oracle Database. Both options are performed with a single command.

The `rhptcl upgrade database` command performs a traditional upgrade incurring downtime. The `rhptcl zdtupgrade database` command performs an Oracle RAC or Oracle RAC One Node upgrade with minimal or no downtime.

Use the `rhptcl upgrade database` command to upgrade to Oracle Database 12c release 1 (12.1.0.2) from Oracle Database 11g release 2 (11.2.0.3 and 11.2.0.4). Upgrading to Oracle Database 12c release 2 (12.2.0.1) is supported from Oracle Database 11g release 2 (11.2.0.3 and 11.2.0.4) and Oracle Database 12c release 1 (12.1.0.2).

 **Note:**

The version of Oracle Grid Infrastructure on which the pre-upgrade database is running must be the same version or higher than the version of the database to which you are upgrading.

The destination for the upgrade can be a working copy already provisioned, or you can choose to create the working copy of gold image as part of this operation.

The pre-upgrade database can be running on a working copy (a managed home that was provisioned by Fleet Patching and Provisioning) or on an unmanaged home. In the first case, you can roll back the upgrade process with a single RHPCTL command.

 **Note:**

You can delete the source working copy at any time after completing an upgrade. Once you delete the working copy, however, you cannot perform a rollback. Also, use the `rhctl delete workingcopy` command (as opposed to `rm`, for example) to remove the source working copy to keep the Fleet Patching and Provisioning inventory correct.

Related Topics

- [rhctl upgrade database](#)
- [rhctl zdtupgrade database](#)

Combined Oracle Exadata Database Node and Grid Infrastructure Patching

With combined Oracle Exadata database node and Oracle Grid Infrastructure patching you can utilize the functionality of multiple independent capabilities.

Using the combined functionality reduces the overall time for patching and minimizes the restarting of database resources. The functionality includes:

- The `patchmgr` tool to perform Oracle Exadata database node patching
- The Oracle Fleet Patching and Provisioning (FPP) tools to perform Oracle Grid Infrastructure patching

To complete combined Oracle Exadata database node and Oracle Grid Infrastructure patching, you must perform the operations discussed in the following:

- [Creating the Oracle Exadata Patch Image](#)
- [Deploying the Oracle Exadata Patch Image](#)
- [Combined Oracle Grid Infrastructure Move and Database Node Update](#)
- [Patching an Oracle Exadata System](#)

Creating the Oracle Exadata Patch Image

Use the `rhpctl import image` command to create the Oracle Exadata patch image by copying the entire software contents from the specified path to the Oracle Fleet Patching and Provisioning Server (FPPS).

Example 2-1 Creating an Oracle Exadata image

The following command creates an Oracle Exadata image. In the example, `image` specifies the name of the Oracle Exadata image that you want to add, `path` specifies the absolute path location of the Oracle Exadata software home that you want to import, `imagetype` specifies `EXAPATCHSOFTWARE` for Oracle Exadata software, and `version` specifies the version of the Oracle Exadata software.

```
$ rhpctl import image -image EXADATAIMAGEV1
  -path /tmp/ExadataPatchBundle -imagetype EXAPATCHSOFTWARE -version
19.2.2.0.0.190513.2
```

When you import an Oracle Exadata software home with this command, the `version` parameter must be the version of the Oracle Exadata software required by the `patchmgr` on the database node. The `path` parameter should contain Oracle Exadata patch zip files.

See Also:

[rhpctl import image](#) for the complete syntax of the `rhpctl import image` command

Deploying the Oracle Exadata Patch Image

Use the `rhpctl deploy image` command to propagate the Oracle Exadata patch image to targets.

Example 2-2 Deploying an Oracle Exadata image

The following command deploys an Oracle Exadata image to a client cluster. In the example, `image` specifies the name of the Oracle Exadata image that you want to deploy, `client` specifies the name of the cluster to which you want to deploy the image, and `path` specifies the absolute path location for deploying the Oracle Exadata software home on the target or client side.

```
$ rhpctl deploy image -image EXADATAIMAGEV1 -client CLUSTER1 -path /
exadatasoftware
```

The `targetnode` parameter is required if the node hosting the home is not a Oracle Fleet Patching and Provisioning Client. If the target node or client option is not specified, then the Oracle Exadata image is deployed to the Oracle Fleet Patching and Provisioning Server.

**See Also:**

[rhpctl deploy image](#) for the complete syntax of the `rhpctl deploy image` command

Combined Oracle Grid Infrastructure Move and Database Node Update

Use the `rhpctl move gihome` command to move the Oracle Grid Infrastructure software stack from one home to another while updating the Oracle Exadata database node.

Example 2-3 Moving an Oracle Grid Infrastructure home and updating a database node

The following example performs a combined Oracle Grid Infrastructure move and database node patching on client cluster. In the example, `sourcewc` specifies the name of the source working copy, `destwc` specifies the name of the destination working copy to which you want to move the Oracle Grid Infrastructure home, `image` specifies the name of the Oracle Exadata image, `batches` specifies a comma-delimited list of batches of nodes where each batch is a comma-delimited list of node names enclosed in parentheses and node names are enclosed in double quotation marks (") in the format: "(nA,nB,...),(... ,nY,nZ)", `iso_repo` specifies the image in the ISO repository, and `patchmgrloc` specifies the patch manager location.

```
$ rhpctl move gihome -sourcewc prodHomeV1 -destwc prodHomeV2 -image
EXADATAIMAGEV1
    -batches "(rac07box1,rac07box2,rac07box3),(rac07box4)"
    -iso_repo p28802055_192000_Linux-x86-64.zip -client prodcluster
    -patchmgrloc /patchMgr/dbserver_patch_19.190306
```

With each invocation of the `rhpctl move gihome` command, FPP patches the database node first and then patches Oracle Grid Infrastructure. This is the processing order for each node in the specified batch.

If the first batch includes more than one database node, then FPP invokes `patchmgr` in parallel for all the nodes. As soon as a node completes the `patchmgr` operation, including the post `patchmgr` operations, FPP starts the Oracle Grid Infrastructure patching on that node. When the Oracle Grid Infrastructure patching completes on this node, FPP then begins patching with Oracle Grid Infrastructure patching on the other nodes when the database node patching completes on those nodes.

If rebooting a node is delayed because of a `patchmgr` failure or a `patchmgr` operation timeout, the `rhpctl move gihome` command can be resumed after the node is back up.

**See Also:**

[rhpctl move gihome](#) for the complete syntax of the `rhpctl move gihome` command

Patching an Oracle Exadata System

Use the `rhpctl update exadata` command to perform the Oracle Exadata database node patching.

Example 2-4 Patching an Oracle Exadata system

The following example performs database node patching on a client cluster. In the example, `image` specifies the name of the Oracle Exadata image that you want to use for patching, `pathmgrloc` specifies the patch manager location, `iso_repo` specifies the image in the ISO repository, `client` specifies the name of the cluster in which you want to update database nodes, and `batches` specifies a comma-delimited list of batches of nodes where each batch is a comma-delimited list of node names enclosed in parentheses and node names are enclosed in double quotation marks (" ") in the format: "(nA,nB,...),(...,nY,nZ)".

```
$ rhpctl update exadata image -image EXADATAIMAGEV1
  -iso_repo p28802055_192000_Linux-x86-64.zip
  -patchmgrloc /patchMgr/dbserver_patch_19.190306 -client CLIENT1 -
batches "(rac07box1)"
```

If the `client` option is not specified when issuing the command, then database node update is performed on the Oracle Fleet Patching and Provisioning Server.

See Also:

[rhpctl update exadata](#) for the complete syntax of the `rhpctl update exadata` command

Zero-Downtime Upgrade

Using Oracle Fleet Patching and Provisioning, which automates and orchestrates database upgrades, you can upgrade an Oracle RAC or Oracle RAC One Node database with no disruption in service.

The zero-downtime upgrade process is resumable, restartable, and recoverable should any errors interrupt the process. You can fix the issue then re-run the command, and Oracle Fleet Patching and Provisioning continues from the error point. Oracle also provides hooks at the beginning and end of the zero-downtime upgrade process, allowing call outs to user-defined scripts, so you can customize the process.

Note:

A multitenant container database is the only supported architecture in Oracle Database 21c. While the documentation is being revised, legacy terminology may persist. In most cases, "database" and "non-CDB" refer to a CDB or PDB, depending on context. In some contexts, such as upgrades, "non-CDB" refers to a non-CDB from a previous release.

You can use the zero-downtime upgrade process to upgrade databases that meet the following criteria:

- **Database upgrade targets:** Oracle RAC and Oracle RAC One Node, with the following upgrade paths:
 - 11.2.0.4 to: 12.1.0.2, 12.2, 18c
 - 12.1.0.2 to: 12.2, 18c - 21c
 - 12.2 to: 18c - 21c
 - 18c to: 19c - 21c
 - 19c to: 21c
- **Oracle Fleet Patching and Provisioning management:** The source database home can either be unmanaged (not provisioned by Oracle Fleet Patching and Provisioning service) or managed (provisioned by Oracle Fleet Patching and Provisioning service)
- **Database state:** The source database must be in archive log mode

Upgrading Container Databases

You can use Oracle Fleet Patching and Provisioning to upgrade CDBs but Oracle Fleet Patching and Provisioning does not support converting a non-CDB to a CDB during upgrade. To prepare for a zero-downtime upgrade, you complete configuration steps and validation checks. When you run a zero-downtime upgrade using Oracle Fleet Patching and Provisioning, you can stop the upgrade and resume it, if necessary. You can recover from any upgrade errors, and you can restart the upgrade. You also have the ability to insert calls to your own scripts during the upgrade, so you can customize your upgrade procedure.

Zero-Downtime Upgrade Environment Prerequisites

- **Server environment:** Oracle Grid Infrastructure 18c - 21c with Oracle Fleet Patching and Provisioning
- **Database hosts:** Databases hosted on one of the following platforms:
 - Oracle Grid Infrastructure 18c - 21c Fleet Patching and Provisioning, Client or Server
 - Oracle Grid Infrastructure 12c (12.2.0.1) Fleet Patching and Provisioning Client
 - Oracle Grid Infrastructure 12c (12.1.0.2) target cluster
- **Database-specific prerequisites for the environment:** During an upgrade, Oracle Fleet Patching and Provisioning manages replication to a local data file to preserve transactions applied to the new database when it is ready. There are two possibilities for the local data file:
 - Snap clone, which is available if the database data files and redo and archive redo logs are on Oracle ACFS file systems
 - Full copy, for all other cases
- Oracle Fleet Patching and Provisioning requires either Oracle GoldenGate or Oracle Data Guard during a zero-downtime database upgrade. As part of the upgrade procedure, Oracle Fleet Patching and Provisioning configures and manages the Oracle GoldenGate deployment.

Running a Zero-Downtime Upgrade Using Oracle GoldenGate for Replication

Run a zero-downtime upgrade using Oracle GoldenGate for replication.

1. Prepare the Fleet Patching and Provisioning Server.

Create gold images of the Oracle GoldenGate software in the image library of the Fleet Patching and Provisioning Server.

Note:

You can download the Oracle GoldenGate software for your platform from Oracle eDelivery. The Oracle GoldenGate 12.3 installable kit contains the required software for both Oracle Database 11g and Oracle Database 12c databases.

If you download the Oracle GoldenGate software, then extract the software home and perform a *software only* installation on the Fleet Patching and Provisioning Server.

Create gold images of the Oracle GoldenGate software for both databases, as follows:

```
$ rhpctl import image -image 112ggimage -path path -imagetype  
ORACLEGGSOFTWARE  
$ rhpctl import image -image 12ggimage -path path -imagetype  
ORACLEGGSOFTWARE
```

In both of the preceding commands, *path* refers to the location of the Oracle GoldenGate software home on the Fleet Patching and Provisioning Server for each release of the database.

2. Prepare the target database.

Provision working copies of the Oracle GoldenGate software to the cluster hosting the database, as follows:

```
$ rhpctl add workingcopy -workingcopy GG_Wcopy_11g -image  
112ggimage -user  
  user_name -node 12102_cluster_node -path path {-root | -sudouser  
user_name  
  -sudopath sudo_bin_path}  
$ rhpctl add workingcopy -workingcopy GG_Wcopy_12c -image 12ggimage  
-user  
  user_name -node 12102_cluster_node -path path {-root | -sudouser  
user_name  
  -sudopath sudo_bin_path}
```

If the database is hosted on the Fleet Patching and Provisioning Server, itself, then neither the *-targetnode* nor *-client* parameters are required.

 **Note:**

Working copy names must be unique, therefore you must use a different working copy name on subsequent targets. You can create unique working copy names by including the name of the target/client cluster name in the working copy name.

3. Provision a working copy of the Oracle Database 12c software home to the target cluster.

 **Note:**

You can do this preparation ahead of the maintenance window without disrupting any operations taking place on the target.

- You can run the upgrade command on the Fleet Patching and Provisioning Server to upgrade a database hosted on the server, an Oracle Database 12c release 1 (12.1.0.2) target cluster, or a database hosted on a Fleet Patching and Provisioning Client 12c release 2 (12.2.0.1) or 18c. You can also run the command a Fleet Patching and Provisioning Client 18c to upgrade a database hosted on the client, itself.

Use the upgrade command similar to the following:

```
$ rhpctl zdtupgrade database -dbname sierra -destwc DB_Wcopy_121  
-gsrcwc  
  GG_Wcopy_11g -ggdstwc GG_Wcopy_12c -targetnode 12102_cluster_node  
-root
```

In the preceding command, *12102_cluster_node* refers to the Oracle Grid Infrastructure 12c release 1 (12.1.0.2) cluster hosting the database you want to upgrade.

Related Topics

- [rhpctl import image](#)
Creates an image on the Fleet Patching and Provisioning Server.
- [rhpctl add workingcopy](#)
Creates a working copy on a client cluster.
- [rhpctl zdtupgrade database](#)
The Zero Downtime Upgrade command `rhpctl zdtupgrade database` enables zero downtime database upgrades for Oracle RAC and Oracle RAC One Node Oracle Database instances.

Running a Zero-Downtime Upgrade Using Oracle Data Guard for Replication

Run a zero-downtime upgrade using Oracle Data Guard for replication.

You can run the zero-downtime upgrade command using Oracle Data Guard's transient logical standby (TLS) feature. All of the steps involved are orchestrated by the zero-downtime upgrade command.

After you provision the destination database Home, the following prerequisites must be met:

- Data Guard Broker is not enabled
- Flash recovery area (FRA) is configured
- The following example of a zero-downtime upgrade using Oracle Data Guard upgrades an Oracle Database 11g release 2 (11.2.0.4), `sierra`, running on the target cluster, which includes a node, `targetclust003`, to an Oracle Database 12c release 1 (12.1.0.2) (the destination working copy, which was provisioned from a Gold Image stored on the Fleet Patching and Provisioning Server named `rhps.example.com`):

```
$ rhpctl zdtupgrade database -dbname sierra -destwc WC121DB4344 -
clonedatadg DBDATA -targetnode node90743 -root
```

```
Enter user "root" password:
node90753.example.com: starting zero downtime upgrade operation ...
node90753.example.com: verifying patches applied to Oracle homes ...
node90753.example.com: verifying if database "sierra" can be
upgraded with zero downtime ...
node90743: 15:09:10.459: Verifying whether database "sierra" can be
cloned ...
node90743: 15:09:10.462: Verifying that database "sierra" is a
primary database ...
node90743: 15:09:14.672: Verifying that connections can be created
to database "sierra" ...
< ... >
node90743: 15:14:58.015: Starting redo apply ...
node90743: 15:15:07.133: Configuring primary database "sierra" ...
#####
node90753.example.com: retrieving information about database
"xmvo tkvd" ...
node90753.example.com: creating services for snapshot database
"xmvo tkvd" ...
#####
node90743: 15:15:33.640: Macro step 1: Getting information and
validating setup ...
< ... >
node90743: 15:16:02.844: Macro step 2: Backing up user environment
in case upgrade is aborted ...
node90743: 15:16:02.848: Stopping media recovery for database
"xmvo tkvd" ...
node90743: 15:16:05.858: Creating initial restore point
"NZDRU_0000_0001" ...
```

```
< ... >
node90743: 15:16:17.611: Macro step 3: Creating transient logical
standby from existing physical standby ...
node90743: 15:16:18.719: Stopping instance "xmvtkvd2" of database
"xmvtkvd" ...
node90743: 15:16:43.187: Verifying that database "sierra" is a
primary database ...
< ... >
node90743: 15:19:27.158: Macro step 4: Upgrading transient logical
standby database ...
node90743: 15:20:27.272: Disabling service "sierrasvc" of database
"xmvtkvd" ...
node90743: 16:36:54.684: Macro step 5: Validating upgraded
transient logical standby database ...
node90743: 16:37:09.576: Creating checkpoint "NZDRU_0301" for
database "xmvtkvd" during stage "3" and task "1" ...
node90743: 16:37:09.579: Stopping media recovery for database
"xmvtkvd" ...
node90743: 16:37:10.792: Creating restore point "NZDRU_0301" for
database "xmvtkvd" ...
node90743: 16:37:11.998: Macro step 6: Switching role of transient
logical standby database ...
node90743: 16:37:12.002: Verifying that database "sierra" is a
primary database ...
< ... >
node90743: 16:39:07.425: Macro step 7: Flashback former primary
database to pre-upgrade restore point and convert to physical
standby ...
node90743: 16:39:08.833: Stopping instance "sierra2" of database
"sierra" ...
< ... >
node90743: 16:41:17.138: Macro step 8: Recovering former primary
database ...
node90743: 16:41:19.045: Verifying that database "sierra" is
mounted ...
< ... >
node90743: 17:20:21.378: Macro step 9: Switching back ...
< ... >
#####
node90753.example.com: deleting snapshot database "xmvtkvd" ...
```

Customizing Zero-Downtime Upgrades

You can customize zero-downtime upgrades using the user-action framework of Fleet Patching and Provisioning.

To use the user-action framework, you can provide a separate script for any or all of the points listed in the overall process.

Table 2-1 Zero-Downtime Upgrade Plugins

Plugin Type	Pre or Post	Plugin runs...
ZDTUPGRADE_DATABASE	Pre	Before Fleet Patching and Provisioning starts zero-downtime upgrade.
	Post	After Fleet Patching and Provisioning completes zero-downtime upgrade.
ZDTUPGRADE_DATABASE_SNAPDB	Pre	Before creating the snapshot or full-clone database.
	Post	After starting the snapshot or full-clone database (but before switching over).
ZDTUPGRADE_DATABASE_DBUA	Pre	Before running DBUA (after switching over).
	Post	After DBUA completes.
ZDTUPGRADE_DATABASE_SWITCHBACK	Pre	Before switching back users to the upgraded source database.
	Post	After switching back users to the upgraded source database (before deleting snapshot or full-clone database).

- To register a plugin to be run during a zero-downtime upgrade, run the following command:

```
$ rhpctl add useraction -useraction user_action_name -actionscript
script_name
  {-pre | -post} -optype {ZDTUPGRADE_DATABASE |
ZDTUPGRADE_DATABASE_SNAPDB |
ZDTUPGRADE_DATABASE_DBUA | ZDTUPGRADE_DATABASE_SWITCHBACK}
```

You can specify run-time input to the plugins using the `-useractiondata` option of the `rhpctl zdtupgrade database` command.

Persistent Home Path During Patching

Oracle recommends out-of-place patching when applying updates.

Out-of-place patching involves deploying the patched environment in a new directory path and then switching the software home to the new path. This approach allows for non-disruptive software distribution because the existing home remains active while the new home is provisioned, and also facilitates rollback because the unpatched software home is available should any issues arise after the switch. Additionally, out-of-place patching for databases enables you to choose to move a subset of instances to the new home if more than one instance is running on the home, whereas with in-place patching, you must patch all instances at the same time.

A potential impediment to traditional out-of-place patching is that the software home path changes. While Oracle Fleet Patching and Provisioning manages this internally and transparently for Oracle Database and Oracle Grid Infrastructure software, some users have developed scripts which depend on the path. To address this, Oracle Fleet Patching and Provisioning uses a file system feature that enables separation of gold image software from the site-specific configuration changes, so the software home path is persistent throughout updates.

This feature is available with Oracle Database 12c release 2 (12.2) and Oracle Grid Infrastructure 12c release 2 (12.2) working copies provisioned in local storage. Also, if you provision an Oracle Database 12c release 2 (12.2) or an Oracle Grid Infrastructure 12c release 2 (12.2) home without using this feature, then, during a patching operation using either the `rhptl move database` or `rhptl move gihome` command, you can convert to this configuration and take advantage of the feature.

 **Note:**

You can only patch Oracle Grid Infrastructure on an Oracle Fleet Patching and Provisioning Client with a home that is based on a persistent home path from an Oracle Fleet Patching and Provisioning Server.

User-Defined Actions

You can create actions for various Oracle Fleet Patching and Provisioning operations, such as import image, add and delete working copy, and add, delete, move, and upgrade a software home.

You can create actions for various Oracle Fleet Patching and Provisioning operations, such as import image, add and delete working copy of a gold image, and add, delete, move, and upgrade a software home. You can define different actions for each operation, which can be further differentiated by the type of image to which the operation applies. User-defined actions can be run before or after a given operation, and are run on the deployment on which the operation is run, whether it be an Oracle Fleet Patching and Provisioning Server, an Oracle Fleet Patching and Provisioning Client (12c release 2 (12.2), or later), or a target that is not running an Oracle Fleet Patching and Provisioning Client.

User-defined actions are shell scripts which are stored on the Oracle Fleet Patching and Provisioning Server. When a script runs, it is given relevant information about the operation on the command line. Also, you can associate a file with the script. The Oracle Fleet Patching and Provisioning Server will copy that file to the same location on the Client or target where the script is run.

For example, perhaps you want to create user-defined actions that are run after a database upgrade, and you want to define different actions for Oracle Database 11g and 12c. This requires you to define new image types, as in the following example procedure.

1. Create a new image type, (`DB11IMAGE`, for example), based on the `ORACLEDBSOFTWARE` image type, as follows:

```
$ rhptl add imagetype -imagetype DB11IMAGE -basetype  
ORACLEDBSOFTWARE
```

When you add or import an Oracle Database 11g gold image, you specify the image type as `DB11IMAGE`.

2. Define a user action and associate it with the `DB11IMAGE` image type and the upgrade operation. You can have different actions that are run before or after upgrade.

- To define an action for Oracle Database 12c, create a new image type (DB12IMAGE, for example) that is based on the ORACLEDBSOFTWARE image type, as in the preceding step, but with the DB12IMAGE image type.

 **Note:**

If you define user actions for the base type of a user-defined image type (in this case the base type is ORACLEDBSOFTWARE), then Oracle Fleet Patching and Provisioning performs those actions before the actions for the user-defined image type.

You can modify the image type of an image using the `rhpcctl modify image` command. Additionally, you can modify, add, and delete other actions. The following two tables, [Table 2-2](#) and [Table 2-3](#), list the operations you can customize and the parameters you can use to define those operations, respectively.

Table 2-2 Oracle Fleet Patching and Provisioning User-Defined Operations

Operation	Parameter List
IMPORT_IMAGE	RHP_OPTYPE, RHP_PHASE, RHP_PATH, RHP_PATHOWNER, RHP_PROGRESSLISTENERHOST, RHP_PROGRESSLISTENERPORT, RHP_IMAGE, RHP_IMAGETYPE, RHP_VERSION, RHP_CLI, RHP_USERACTIONDATA
ADD_WORKINGCOPY	RHP_OPTYPE, RHP_PHASE, RHP_WORKINGCOPY, RHP_PATH, RHP_STORAGETYPE, RHP_USER, RHP_NODES, RHP_ORACLEBASE, RHP_DBNAME, RHP_PROGRESSLISTENERHOST, RHP_PROGRESSLISTENERPORT, RHP_IMAGE, RHP_IMAGETYPE, RHP_VERSION, RHP_CLI, RHP_USERACTIONDATA
ADD_DATABASE	RHP_OPTYPE, RHP_PHASE, RHP_WORKINGCOPY, RHP_CLIENT, RHP_DBNAME, RHP_PROGRESSLISTENERHOST, RHP_PROGRESSLISTENERPORT, RHP_IMAGE, RHP_IMAGETYPE, RHP_VERSION, RHP_CLI, RHP_USERACTIONDATA
DELETE_WORKINGCOPY	RHP_OPTYPE, RHP_PHASE, RHP_WORKINGCOPY, RHP_CLIENT, RHP_PATH, RHP_PROGRESSLISTENERHOS, RHP_PROGRESSLISTENERPORT, RHP_IMAGE, RHP_IMAGETYPE, RHP_VERSION, RHP_CLI, RHP_USERACTIONDATA
DELETE_DATABASE	RHP_OPTYPE, RHP_PHASE, RHP_WORKINGCOPY, RHP_CLIENT, RHP_DBNAME, RHP_PROGRESSLISTENERHOST, RHP_PROGRESSLISTENERPORT, RHP_IMAGE, RHP_IMAGETYPE, RHP_VERSION, RHP_CLI, RHP_USERACTIONDATA
MOVE_GIHOME	RHP_OPTYPE, RHP_PHASE, RHP_SOURCEWC, RHP_SOURCEPATH, RHP_DESTINATIONWC, RHP_DESTINATIONPATH, RHP_IMAGE, RHP_IMAGETYPE, RHP_PROGRESSLISTENERHOS, RHP_PROGRESSLISTENERPORT, RHP_VERSION, RHP_CL, RHP_USERACTIONDATA

Table 2-2 (Cont.) Oracle Fleet Patching and Provisioning User-Defined Operations

Operation	Parameter List
<p>MOVE_DATABASE</p> <p>This user action is run for each database involved in a patching operation.</p> <p>If the run scope is set to ALLNODES, then the script is run for each database on every cluster node.</p> <p>If the run scope is set to ONENODE, then the script is run for each database on the node on which the patch was applied to the database.</p>	RHP_OPTYPE, RHP_PHASE, RHP_SOURCEWC, RHP_SOURCEPATH, RHP_DESTINATIONWC, RHP_DESTINATIONPATH, RHP_DBNAME, RHP_IMAGE, RHP_IMAGETYPE, RHP_PROGRESSLISTENERHOST, RHP_PROGRESSLISTENERPORT, RHP_VERSION, RHP_CLI, RHP_DATAPATCH, RHP_USERACTIONDATA
UPGRADE_GIHOME	RHP_OPTYPE, RHP_PHASE, RHP_SOURCEWC, RHP_SOURCEPATH, RHP_DESTINATIONWC, RHP_DESTINATIONPATH, RHP_IMAGE, RHP_IMAGETYPE, RHP_PROGRESSLISTENERHOST, RHP_PROGRESSLISTENERPORT, RHP_VERSION, RHP_CLI, RHP_USERACTIONDATA
UPGRADE_DATABASE	RHP_OPTYPE, RHP_PHASE, RHP_SOURCEWC, RHP_SOURCEPATH, RHP_DESTINATIONWC, RHP_DESTINATIONPATH, RHP_DBNAME, RHP_IMAGE, RHP_IMAGETYPE, RHP_PROGRESSLISTENERHOST, RHP_PROGRESSLISTENERPORT, RHP_VERSION, RHP_CLI, RHP_USERACTIONDATA
ADDNODE_DATABASE	RHP_OPTYPE, RHP_PHASE, RHP_WORKINGCOPY, RHP_CLIENT, RHP_DBNAME, RHP_PROGRESSLISTENERHOST, RHP_PROGRESSLISTENERPORT, RHP_IMAGE, RHP_IMAGETYPE, RHP_VERSION, RHP_CLI, RHP_USERACTIONDATA
DELETENODE_DATABASE	RHP_OPTYPE, RHP_PHASE, RHP_WORKINGCOPY, RHP_CLIENT, RHP_DBNAME, RHP_PROGRESSLISTENERHOST, RHP_PROGRESSLISTENERPORT, RHP_IMAGE, RHP_IMAGETYPE, RHP_VERSION, RHP_CLI, RHP_USERACTIONDATA
ADDNODE_GIHOME	RHP_OPTYPE, RHP_PHASE, RHP_WORKINGCOPY, RHP_CLIENT, RHP_PATH, RHP_PROGRESSLISTENERHOST, RHP_PROGRESSLISTENERPORT, RHP_IMAGE, RHP_IMAGETYPE, RHP_VERSION, RHP_CLI, RHP_USERACTIONDATA
DELETENODE_GIHOME	RHP_OPTYPE, RHP_PHASE, RHP_WORKINGCOPY, RHP_CLIENT, RHP_PATH, RHP_PROGRESSLISTENERHOST, RHP_PROGRESSLISTENERPORT, RHP_IMAGE, RHP_IMAGETYPE, RHP_VERSION, RHP_CLI, RHP_USERACTIONDATA
ADDNODE_WORKINGCOPY	RHP_OPTYPE, RHP_PHASE, RHP_WORKINGCOPY, RHP_CLIENT, RHP_PATH, RHP_PROGRESSLISTENERHOST, RHP_PROGRESSLISTENERPORT, RHP_IMAGE, RHP_IMAGETYPE, RHP_VERSION, RHP_CLI, RHP_USERACTIONDATA

Table 2-2 (Cont.) Oracle Fleet Patching and Provisioning User-Defined Operations

Operation	Parameter List
ZDTUPGRADE_DATABASE	RHP_OPTYPE, RHP_PHASE, RHP_SOURCEWC, RHP_SOURCEPATH, RHP_DESTINATIONWC, RHP_DESTINATIONPATH, RHP_SRCGGWC, RHP_SRCGGPATH, RHP_DSTGGWC, RHP_DSTGGPATH, RHP_DBNAME, RHP_IMAGE, RHP_IMAGETYPE, RHP_PROGRESSLISTENERHOST, RHP_PROGRESSLISTENERPORT, RHP_VERSION, RHP_CLI, RHP_USERACTIONDATA
ZDTUPGRADE_DATABASE_SNAPDB	RHP_OPTYPE, RHP_PHASE, RHP_SOURCEWC, RHP_SOURCEPATH, RHP_DESTINATIONWC, RHP_DESTINATIONPATH, RHP_SRCGGWC, RHP_SRCGGPATH, RHP_DSTGGWC, RHP_DSTGGPATH, RHP_DBNAME, RHP_IMAGE, RHP_IMAGETYPE, RHP_PROGRESSLISTENERHOST, RHP_PROGRESSLISTENERPORT, RHP_VERSION, RHP_CLI, RHP_USERACTIONDATA
ZDTUPGRADE_DATABASE_DBUA	RHP_OPTYPE, RHP_PHASE, RHP_SOURCEWC, RHP_SOURCEPATH, RHP_DESTINATIONWC, RHP_DESTINATIONPATH, RHP_SRCGGWC, RHP_SRCGGPATH, RHP_DSTGGWC, RHP_DSTGGPATH, RHP_DBNAME, RHP_IMAGE, RHP_IMAGETYPE, RHP_PROGRESSLISTENERHOST, RHP_PROGRESSLISTENERPORT, RHP_VERSION, RHP_CLI, RHP_USERACTIONDATA
ZDTUPGRADE_DATABASE_SWITCHBACK	RHP_OPTYPE, RHP_PHASE, RHP_SOURCEWC, RHP_SOURCEPATH, RHP_DESTINATIONWC, RHP_DESTINATIONPATH, RHP_SRCGGWC, RHP_SRCGGPATH, RHP_DSTGGWC, RHP_DSTGGPATH, RHP_DBNAME, RHP_IMAGE, RHP_IMAGETYPE, RHP_PROGRESSLISTENERHOST, RHP_PROGRESSLISTENERPORT, RHP_VERSION, RHP_CLI, RHP_USERACTIONDATA

Table 2-3 User-Defined Operations Parameters

Parameter	Description
RHP_OPTYPE	The operation type for which the user action is being executed, as listed in the previous table.
RHP_PHASE	This parameter indicates whether the user action is executed before or after the operation (is either PRE or POST).
RHP_SOURCEWC	The source working copy name for a patch of upgrade operation.
RHP_SOURCEPATH	The path of the source working copy home.
RHP_DESTINATIONWC	The destination working copy name for a patch or upgrade operation.
RHP_DESTINATIONPATH	The path of the destination working copy home.
RHP_SRCGGWC	The name of the version of the Oracle GoldenGate working copy from which you want to upgrade.
RHP_SRCGGPATH	The absolute path of the version of the Oracle GoldenGate software home from which you want to upgrade.
RHP_DESTGGWC	The name of the version of the Oracle GoldenGate working copy to which you want to upgrade.

Table 2-3 (Cont.) User-Defined Operations Parameters

Parameter	Description
RHP_DESTGGPATH	The absolute path of the version of the Oracle GoldenGate software home to which you want to upgrade.
RHP_PATH	This is the path to the location of the software home. This parameter represents the path on the local node from where the RHPCTL command is being run for an <code>IMPORT_IMAGE</code> operation. For all other operations, this path is present on the site where the operation is taking place.
RHP_PATHOWNER	The owner of the path for the gold image that is being imported.
RHP_PROGRESSLISTENERHOST	The host on which the progress listener is listening. You can use this parameter, together with a progress listener port, to create a TCP connection to print output to the console on which the RHPCTL command is being run.
RHP_PROGRESSLISTENERPORT	The port on which the progress listener host is listening. You can use this parameter, together with a progress listener host name, to create a TCP connection to print output to the console on which the RHPCTL command is being run.
RHP_IMAGE	The image associated with the operation. In the case of a move operation, it will reflect the name of the destination image.
RHP_IMAGETYPE	The image type of the image associated with the operation. In the case of a move operation, it will reflect the name of the destination image.
RHP_VERSION	The version of the Oracle Grid Infrastructure software running on the Oracle Fleet Patching and Provisioning Server.
RHP_CLI	The exact command that was run to invoke the operation.
RHP_STORAGETYPE	The type of storage for the home (either <code>LOCAL</code> or <code>RHP_MANAGED</code>)
RHP_USER	The user for whom the operation is being performed.
RHP_NODES	The nodes on which a database will be created.
RHP_ORACLEBASE	The Oracle base location for the provisioned home.
RHP_DBNAME	The name of the database to be created.
RHP_CLIENT	The name of the client cluster.
RHP_DATAPATCH	This parameter is set to <code>TRUE</code> at the conclusion of the user action on the node where the SQL patch will be run after the move database operation is complete.
RHP_USERACTIONDATA	This parameter is present in all of the operations and is used to pass user-defined items to the user action as an argument during runtime.

Example of User-Defined Action

Suppose there is an image type, `APACHESW`, to use for provisioning and managing Apache deployments. Suppose, too, that there is a Gold Image of Apache named `apacheinstall`. The following example shows how to create a user action that will run prior to provisioning any copy of our Apache Gold Image.

The following is a sample user action script named `addapache_useraction.sh`:

```
$ cat /scratch/apacheadmin/addapache_useraction.sh
#!/bin/sh

#refer to arguments using argument names
touch /tmp/SAMPLEOUT.txt;
for i in "$@"
do
    export $i
done

echo "OPTYPE = $RHP_OPTYPE" >> /tmp/SAMPLEOUT.txt;
echo "PHASE = $RHP_PHASE" >> /tmp/SAMPLEOUT.txt;
echo "WORKINGCOPY = $RHP_WORKINGCOPY" >> /tmp/SAMPLEOUT.txt;
echo "PATH = $RHP_PATH" >> /tmp/SAMPLEOUT.txt;
echo "STORAGETYPE = $RHP_STORAGETYPE" >> /tmp/SAMPLEOUT.txt;
echo "USER = $RHP_USER" >> /tmp/SAMPLEOUT.txt;
echo "NODES = $RHP_NODES" >> /tmp/SAMPLEOUT.txt;
echo "ORACLEBASE = $RHP_ORACLEBASE" >> /tmp/SAMPLEOUT.txt;
echo "DBNAME = $RHP_DBNAME" >> /tmp/SAMPLEOUT.txt;
echo "PROGRESSLISTENERHOST = $RHP_PROGRESSLISTENERHOST" >> /tmp/
SAMPLEOUT.txt;
echo "PROGRESSLISTENERPORT = $RHP_PROGRESSLISTENERPORT" >> /tmp/
SAMPLEOUT.txt;
echo "IMAGE = $RHP_IMAGE" >> /tmp/SAMPLEOUT.txt;
echo "IMAGETYPE = $RHP_IMAGETYPE" >> /tmp/SAMPLEOUT.txt;
echo "RHPVERSION = $RHP_VERSION" >> /tmp/SAMPLEOUT.txt;
echo "CLI = $RHP_CLI" >> /tmp/SAMPLEOUT.txt;
echo "USERACTIONDATA = $RHP_USERACTIONDATA" >> /tmp/SAMPLEOUT.txt;
$
```

The script is registered to run at the start of `rhpcctl add workingcopy` commands. The `add working copy` operation aborts if the script fails.

The following command creates a user action called `addapachepre`:

```
$ rhpcctl add useraction -optype ADD_WORKINGCOPY -pre -onerror ABORT
-useraction
    addapachepre -actionscript /scratch/apacheadmin/
addapache_useraction.sh
    -runscope ONENODE
```

The following command registers the user action for the `APACHESW` image type:

```
$ rhpcctl modify imagetype -imagetype APACHESW -useractions addapachepre
```

The registered user action is invoked automatically at the start of commands that deploy a working copy of any image of the `APACHESW` type, such as the following:

```
$ rhpcctl add workingcopy -workingcopy apachecopy001 -image
apacheinstall
    -path /scratch/apacheadmin/apacheinstallloc -sudouser apacheadmin -
```

```
sudopath
/usr/local/bin/sudo -node targetnode003 -user apacheadmin -
useractiondata "sample"
```

The sample script creates the `/tmp/SAMPLEOUT.txt` output file. Based on the example command, the output file contains:

```
$ cat /tmp/SAMPLEOUT.txt
OPTYPE = ADD_WORKINGCOPY
PHASE = PRE
WORKINGCOPY = apachecopy001
PATH = /scratch/apacheadmin/apacheinstallloc
STORAGETYPE =
USER = apacheadmin
NODES = targetnode003
ORACLEBASE =
DBNAME =
PROGRESSLISTENERHOST = mds11042003.my.company.com
PROGRESSLISTENERPORT = 58068
IMAGE = apacheinstall
IMAGETYPE = APACHESW
RHPVERSION = 12.2.0.1.0
CLI = rhpctl__add__workingcopy__-image__apacheinstall__-path__scratch/
apacheadmin
/apacheinstallloc__-node__targetnode003__-useractiondata__sample__
-sudopath__usr/local/bin/sudo__-workingcopy__apachecopy__-
user__apacheadmin__
-sudouser__apacheadmin__USERACTIONDATA = sample
$
```

Notes:

- In the preceding output example empty values terminate with an equals sign (=).
- The spaces in the command-line value of the `RHP_CLI` parameter are replaced by two underscore characters (`__`) to differentiate this from other parameters.

Job Scheduler for Operations

The Oracle Fleet Patching and Provisioning job scheduler provides you with a mechanism to submit operations at a scheduled time instead of running the command immediately, querying the metadata of the job, and then deleting the job from the repository.

The Oracle Fleet Patching and Provisioning job scheduler includes the following features:

- Enables you to schedule a command to run at a specific point in time by providing the time value

- Performs the job and stores the metadata for the job, along with the current status of the job
- Stores the logs for each of the jobs that have run or are running
- Enables you to query job details (for all jobs or for specific jobs, based on the user roles)
- Deletes jobs
- Authorizes the running, querying, and deleting of jobs, based on role-based access for users

Use the `-schedule timer_value` command parameter with any of the following RHPCTL commands to schedule certain Rapid Hope Provisioning operations:

- `rhpcctl add workingcopy`
- `rhpcctl import image`
- `rhpcctl delete image`
- `rhpcctl add database`
- `rhpcctl move gihome`
- `rhpcctl move database`
- `rhpcctl upgrade database`
- `rhpcctl addnode database`
- `rhpcctl deletenode database`
- `rhpcctl delete workingcopy`

For example:

```
$ rhpcctl add workingcopy -workingcopy 18_3 -image 18_3_Base -  
oraclebase /u01/app/oracle -schedule 2016-12-21T19:13:17+05
```

All commands are run in reference with the time zone of the server, according to the ISO-8601 value, and RHPCTL displays the command result by specifying the same time zone.

Command Results

RHPCTL stores any command that is run from the command queue on the Oracle Fleet Patching and Provisioning Server. When you query a command result by specifying the command identifier, then RHPCTL returns the path to the job output file, along with the results.

Job Operation

When you run an RHPCTL command with the `-schedule` parameter, the operation creates a job with a unique job ID that you can query to obtain the status of the job.

Job Status

At any point in time, a job can be in any of the following states:

```
EXECUTED | TIMER_RUNNING | EXECUTING | UNKNOWN | TERMINATED
```

- EXECUTED: The job is complete.
- TIMER_RUNNING: The timer for the job is still running.
- EXECUTING: The timer for the job has expired and the job is running.
- UNKNOWN: There is an unexpected failure due to issues such as a target going down, nodes going down, or any resource failures.
- TERMINATED: There is an abrupt failure or the operation has stopped.

Related Topics

- [rhpctl delete job](#)
- [rhpctl query job](#)

Oracle Restart Patching and Upgrading

You can use Oracle Fleet Patching and Provisioning to patch and upgrade Oracle Restart using gold images.

You can move the target of single-node Oracle Restart to an Oracle home that you provision from a gold image that includes any patches. Oracle Fleet Patching and Provisioning ensures the copying of the configuration files, such as listener.ora, to the new Oracle home.

You can also use Oracle Fleet Patching and Provisioning to upgrade Oracle Restart using gold images. Upgrade the Oracle Restart environment by upgrading the Oracle home on the target Oracle home that you provision from a higher-level gold image. Oracle Fleet Patching and Provisioning updates the configuration and inventory settings.

Use the RHPCTL utility similar to the following:

```
rhpctl add workingcopy -workingcopy Oracle_Restart_working_copy  
-resposnefile Oracle_Restart_resposne_file -targetnode  
node_on_which_Oracle_Restart_is_provisioned {superuser credentials}
```


3

Managing Oracle Fleet Patching and Provisioning Clients

Management tasks for Oracle Fleet Patching and Provisioning Clients include creation, enabling and disabling, creating users and assigning roles to those users, and managing passwords.

Using SRVCTL and RHPCTL, you can perform all management tasks for an Oracle Fleet Patching and Provisioning Client.

This chapter includes the following topics:

- [Creating a Fleet Patching and Provisioning Client](#)
- [Enabling and Disabling Fleet Patching and Provisioning Clients](#)
- [Deleting a Fleet Patching and Provisioning Client](#)
- [Creating Users and Assigning Roles for Fleet Patching and Provisioning Client Cluster Users](#)
- [Managing the Fleet Patching and Provisioning Client Password](#)

See Also:

- *Oracle Clusterware Administration and Deployment Guide* for information about SRVCTL commands to manage various components and applications in your cluster.
- *Oracle Real Application Clusters Administration and Deployment Guide* for information about SRVCTL commands to manage Oracle Real Application Clusters (Oracle RAC) configuration information.

Creating a Fleet Patching and Provisioning Client

Users operate on a Fleet Patching and Provisioning Client to perform tasks such as requesting deployment of Oracle homes and querying gold images.

To create a Fleet Patching and Provisioning Client:

1. If there is no highly available VIP (HAVIP) on the Fleet Patching and Provisioning Server, then, as the `root` user, create an HAVIP, as follows:

```
# srvctl add havip -id id -address {host_name | ip_address}
```

You can specify either a host name or IPv4 or IPv6 IP address. The IP address that you specify for HAVIP or the address that is resolved from the specified host name *must not* be in use when you run this command.

 **Note:**

The highly available VIP must be in the same subnet as the default network configured in the Fleet Patching and Provisioning Server cluster. You can obtain the subnet by running the following command:

```
$ srvctl config network -netnum 1
```

2. On the Fleet Patching and Provisioning Server as the Grid home owner, create the client data file, as follows:

```
$ rhpctl add client -client client_cluster_name -toclientdata path
```

RHPCTL creates the client data file in the directory path you specify after the `-toclientdata` flag. The name of the client data file is `client_cluster_name.xml`.

 **Note:**

The `client_cluster_name` must be unique and it must match the cluster name of the client cluster where you run step 4.

3. Copy the client data file that you created in the previous step to a directory on the client cluster that has read/write permissions to the Grid home owner on the Fleet Patching and Provisioning Client.
4. Create the Fleet Patching and Provisioning Client by running the following command as `root` on the client cluster:

```
# srvctl add rhpclient -clientdata path_to_client_data  
[-diskgroup disk_group_name -storage base_path]
```

If you want to provision working copies to Oracle ACFS storage on this cluster, and you have already created a disk group for this purpose, then specify this disk group in the preceding command. In this case, also specify a storage path which will be used as a base path for all mount points when creating Oracle ACFS file systems for storing working copies.

 **Note:**

Once you configure a disk group on a Fleet Patching and Provisioning Client, you cannot remove it from or change it in the Fleet Patching and Provisioning Client configuration. The only way you can do either (change or remove) is to completely remove the Fleet Patching and Provisioning Client using the `srvctl remove client` command, and then add it back with a different disk group, if necessary. Before you remove a Fleet Patching and Provisioning Client, ensure that you remove all registered users from this cluster and all working copies provisioned on this cluster.

5. Start the Fleet Patching and Provisioning Client, as follows:

```
$ srvctl start rhpclient
```

6. Check the status of the Fleet Patching and Provisioning Client, as follows:

```
$ srvctl status rhpclient
```

Related Topics

- [Oracle Clusterware Administration and Deployment Guide](#)
- [Oracle Fleet Patching and Provisioning Control \(RHPCTL\) Command Reference](#)
Use the Oracle Fleet Patching and Provisioning Control (RHPCTL) utility to manage Oracle Fleet Patching and Provisioning in your cluster.

Enabling and Disabling Fleet Patching and Provisioning Clients

On the Fleet Patching and Provisioning Server, you can enable or disable a Fleet Patching and Provisioning Client.

Fleet Patching and Provisioning Clients communicate with the Fleet Patching and Provisioning Server for all actions. You cannot run any RHPCTL commands without a connection to a Fleet Patching and Provisioning Server.

To enable or disable a Fleet Patching and Provisioning Client, run the following command from the Fleet Patching and Provisioning Server cluster:

```
$ rhpctl modify client -client client_name -enabled TRUE | FALSE
```

To enable a Fleet Patching and Provisioning Client, specify `-enabled TRUE`. Conversely, specify `-enabled FALSE` to disable the client. When you disable a Fleet Patching and Provisioning Client cluster, all RHPCTL commands from that client cluster will be rejected by the Fleet Patching and Provisioning Server, unless and until you re-enable the client.

**Note:**

Disabling a Fleet Patching and Provisioning Client cluster does not disable any existing working copies on the client cluster. The working copies will continue to function and any databases in those working copies will continue to run.

Deleting a Fleet Patching and Provisioning Client

Use the following procedure to delete a Fleet Patching and Provisioning Client.

1. Before deleting the Fleet Patching and Provisioning Client, you must first delete the working copies and users on the Fleet Patching and Provisioning Server, as follows:

- a. Query the list of working copies that have been provisioned on the Fleet Patching and Provisioning Client cluster.

Run the following command:

```
$ rhpctl query workingcopy -client client_name
```

- b. Delete each of the working copies listed in the output of the preceding command.

Run the following command for each working copy and specify the name of the working copy you want to delete:

```
$ rhpctl delete workingcopy -workingcopy working_copy_name
```

- c. Query the list of users from the Fleet Patching and Provisioning Client cluster.

Run the following command:

```
$ rhpctl query user -client client_name
```

- d. Delete the users listed in the output of the preceding command, as follows:

Run the following command and specify the name of the user you want to delete and the name of the client:

```
$ rhpctl delete user -user user_name -client client_name
```

2. On the Fleet Patching and Provisioning Client cluster, delete the client, as follows:

- a. Stop the Fleet Patching and Provisioning Client daemon.

Run the following command:

```
$ srvctl stop rhpclient
```

- b. Delete the Fleet Patching and Provisioning Client configuration.

Run the following command:

```
$ srvctl remove rhpclient
```

3. Delete the client site configuration on the Fleet Patching and Provisioning Server cluster.

Run the following command and specify the name of the client:

```
$ rhpctl delete client -client client_name
```

Creating Users and Assigning Roles for Fleet Patching and Provisioning Client Cluster Users

When you create a Fleet Patching and Provisioning Client with the `rhpctl add client` command, you can use the `-maproles` parameter to create users and assign roles to them. You can associate multiple users with roles, or you can assign a single user multiple roles with this command.

Note:

Starting with Oracle Grid Infrastructure 21c, the `-maproles` parameter is deprecated. This parameter can be desupported in a future release.

After the client has been created, you can add and remove roles for users using the `rhpctl grant role` command and the `rhpctl revoke role`, respectively.

Managing the Fleet Patching and Provisioning Client Password

The Fleet Patching and Provisioning Client uses a password stored internally to authenticate itself with the RHP server. You cannot query this password, however, if for some reason, you are required to reset this password, then you can do so, as follows, on the RHP server cluster:

1. Run the following command on the Fleet Patching and Provisioning Server cluster to generate a new password and store it in the client credential:

```
$ rhpctl modify client -client client_name -password
```

2. Run the following command on the Fleet Patching and Provisioning Server cluster to generate a credential file:

```
$ rhpctl export client -client client_name -clientdata file_path
```

For example, to generate a credential file for a Fleet Patching and Provisioning Client named `mjk9394`:

```
$ rhpctl export client -client mjk9394 -clientdata /tmp/mjk9394.xml
```

3. Continuing with the preceding example, transport the generated credential file securely to the Fleet Patching and Provisioning Client cluster and then run the

following command on any node in the Fleet Patching and Provisioning Client cluster:

```
$ srvctl modify rhpclient -clientdata path_to_mjk9394.xml
```

4. Restart the Fleet Patching and Provisioning Client daemon by running the following commands on the Fleet Patching and Provisioning Client cluster:

```
$ srvctl stop rhpclient  
$ srvctl start rhpclient
```

4

Oracle Fleet Patching and Provisioning Use Cases

Review these topics for step-by-step procedures to provision, patch, and upgrade your software using Oracle Fleet Patching and Provisioning.

Oracle Fleet Patching and Provisioning is a software lifecycle management solution and helps standardize patching, provisioning, and upgrade of your standard operating environment.

Creating an Oracle Grid Infrastructure 12c Release 2 Deployment

Provision Oracle Grid Infrastructure software on two nodes that do not currently have a Grid home, and then configure Oracle Grid Infrastructure to form a multi-node Oracle Grid Infrastructure installation.

Before You Begin

 **Note:**

Member Clusters, which are part of the Oracle Cluster Domain architecture, are desupported in Oracle Grid Infrastructure 21c.

 **Note:**

Domain Services Cluster (DSC), which is part of the Oracle Cluster Domain architecture, is deprecated in Oracle Grid Infrastructure 21c and can be desupported in a future release.

Provide configuration details for storage, network, users and groups, and node information for installing Oracle Grid Infrastructure in a response file. You can store the response file in any location on the Fleet Patching and Provisioning Server.

You can provision an Oracle Standalone Cluster, Oracle Application Clusters, Oracle Domain Services Cluster, or Oracle Member Clusters. Ensure that the response file has the required cluster configuration details.

Ensure that you have storage, network, and operating system requirements configured as stated in the *Oracle Grid Infrastructure Installation Guide*.

Procedure

- From the Fleet Patching and Provisioning Server, run the command:

```
$ rhpctl add workingcopy -workingcopy GI122 -image  
GI_HOME_12201 -responsefile /u01/app/rhpinfo/GI_12201_install.rsp  
{authentication_option}
```

GI122 is the working copy based on the image GI_HOME_12201

/u01/app/rhpinfo/GI_12201_install.rsp is the response file location.

Cluster Verification Utility checks for preinstallation configuration as per requirements. Fleet Patching and Provisioning configures Oracle Grid Infrastructure.

Oracle Grid Infrastructure 12c release 2 is provisioned as per the settings in the same response file.

During provisioning, if an error occurs, the procedure stops and allows you to fix the error. After fixing the error, you can resume the provisioning operation from where it last stopped.

Watch a video  [Video](#)

Provisioning an Oracle Database Home and Creating a Database

This procedure provisions Oracle Database 12c release 2 (12.2) software and creates Oracle Database instances.

Procedure

- From the Fleet Patching and Provisioning Server, provision the Oracle Database home software:

```
$ rhpctl add workingcopy -image db12201 -path /u01/app/dbusr/  
product/12.2.0/db12201  
-client client_001 -oraclebase /u01/app/dbusr/ -workingcopy db122
```

The command provisions the working copy db122 to the specified path on the cluster client_001, from the image db12201 .

- Create the database instance:

```
$ rhpctl add database -workingcopy db122 -dbname db -dbtype RAC
```

The command creates an Oracle RAC database instance db . You can use the add database command repeatedly to create more instances on the working copy.

Watch a video  [Video](#)

Provisioning a Pluggable Database

You can provision a pluggable database (PDB) on an existing container database (CDB) running in a provisioned database working copy.

After you create a working copy of a gold image, provision that working copy to a target, and create a database as a multitenant CDB, you can add a PDB to the CDB using the `rhpcctl addpdb database` command.

- The following command example creates a PDB called `pdb183` on a CDB called `raccdb183`, which is on a working copy called `wc_db183`:

```
$ rhpcctl addpdb database -workingcopy wc_db183 -cdbName raccdb183  
-pdbName pdb183
```

- Use the `rhpcctl deletepdb database` command to delete a PDB from an existing CDB on a working copy.

The following command example deletes a PDB called `pdb183` on a CDB called `raccdb183`, which is on a working copy called `wc_db183`:

```
$ rhpcctl deletepdb database -workingcopy wc_db183 -cdbName  
raccdb183 -pdbName pdb183
```

Upgrading to Oracle Grid Infrastructure 12c Release 2

This procedure uses Fleet Patching and Provisioning to upgrade your Oracle Grid Infrastructure cluster from 11g release 2 (11.2.0.4) to 12c release 2 (12.2).

Before You Begin

To upgrade to Oracle Grid Infrastructure 12c release 2 (12.2.0.1), your source must be Oracle Grid Infrastructure 11g release 2 (11.2.0.3 or 11.2.0.4), or Oracle Grid Infrastructure 12c release 2 (12.1.0.2).

Ensure that groups configured in the source home match those in the destination home.

Ensure that you have an image `GI_HOME_12201` of the Oracle Grid Infrastructure 12c release 2 (12.2.0.1) software to provision your working copy.

`GI_11204` is the active Grid Infrastructure home on the cluster being upgraded. It is a working copy because in this example, Fleet Patching and Provisioning provisioned the cluster. Fleet Patching and Provisioning can also upgrade clusters whose Grid Infrastructure homes are unmanaged that is, homes that Fleet Patching and Provisioning did not provision.

Procedure

1. Provision a working copy of the Oracle Grid Infrastructure 12c release 2 (12.2.0.1) software:

```
$ rhpcctl add workingcopy -workingcopy GI122 -image GI_HOME_12201  
{authentication_option}
```

GI122 is the working copy based on the image GI_HOME_12201.

2. Upgrade your target cluster to the GI122 working copy:

```
rhpcctl upgrade gihome -sourcewc GI11204 -destwc GI122
```

Rapid Home Provisioning identifies the cluster to upgrade based on the name of the source working copy, and upgrades to the working copy GI122.

Patching Oracle Grid Infrastructure Without Changing the Grid Home Path

This procedure explains how to patch Oracle Grid Infrastructure without changing the Grid home path.

Before You Begin

- Ensure that the gold image containing the Grid home is imported and exists on the Fleet Patching and Provisioning Server.
- Ensure that the directory you provide in the `path` option is not an existing directory.
- The source Grid home must be a managed home (provisioned by Fleet Patching and Provisioning). It does not need to be an Oracle Layered File System (OLFS)-compliant home.
- The Grid home must be Oracle Grid Infrastructure 12c (12.2.0.1) or later.

Procedure for Patching

- To move a non-OLFS-compliant Grid home to an OLFS Grid home, from the Fleet Patching and Provisioning Server, run two commands similar to the following:

```
$ rhpcctl add workingcopy -workingcopy GI_HOME_12201_PSU1 -aupath
/u01/app/orabase/product/12.2.0.1/aupath -image image_name
-client client_name -softwareonly
```

```
$ rhpcctl move gihome -srcwc GI_HOME_12201 -destwc
GI_HOME_12201_PSU1 -agpath
/u01/app/orabase/product/12.2.0.1/agpath -path
/u01/app/orabase/product/12.2.0.1/grid
```

- To move an OLFS-compliant Grid home to a patched version, run two commands similar to the following:

```
$ rhpcctl add workingcopy -workingcopy gihome12201_psu1_lpm -aupath
/u01/app/orabase/product/12.2.0.1/aupath -image image_name -client
client_name -softwareonly
```

```
$ rhpcctl move gihome -sourcewc gihome12201_lpm -destwc
gihome12201_psu1_lpm
```

Patching Oracle Grid Infrastructure and Oracle Databases Simultaneously

This procedure patches Oracle Grid Infrastructure and Oracle Databases on the cluster to the latest patch level without cluster downtime.

Before You Begin

In this procedure, Oracle Grid Infrastructure 12c release 2 (12.2.0.1) is running on the target cluster. Working copy `GI_HOME_12201_WCPY` is the active Grid home on this cluster. Working copy `DB_HOME_12201_WCPY` runs an Oracle RAC 12c release 2 (12.2.0.1) Database with running database instance `db1`. Working copy `DB_HOME_12102_WCPY` runs an Oracle RAC 12c release 1 (12.1.0.2) Database with running database instance `db2`.

Ensure that you have images `GI_HOME_12201_PSU1`, `DB_HOME_12201_PSU1`, `DB_HOME_12102_PSU5` with the required patches for Oracle Grid Infrastructure and Oracle RAC Database on the Fleet Patching and Provisioning Server.

The groups configured in the source home must match with those in the destination home.

Procedure

1. Prepare target Oracle homes as follows:
 - a. Provision software-only Grid home on the cluster to be patched:

```
$ rhpctl add workingcopy -workingcopy GI_HOME_12201_PATCHED_WCPY  
-image GI_HOME_12201_PSU1 -client CLUSTER_005 -softwareonly
```

- b. Provision each release Database home, without database instances, to be patched:

```
$ rhpctl add workingcopy -workingcopy DB_HOME_12201_PATCHED_WCPY  
-image DB_HOME_12201_PSU1  
$ rhpctl add workingcopy -workingcopy DB_HOME_12102_PATCHED_WCPY  
-image DB_HOME_12102_PSU5
```

2. Patch Oracle Grid Infrastructure and all Oracle RAC Databases on `node1` as follows:

```
$ rhpctl move gihome -sourcewc GI_HOME_12201_WCPY -destwc  
GI_HOME_12201_PATCHED_WCPY -auto  
-dbhomes  
DB_HOME_12102_WCPY=DB_HOME_12102_PATCHED_WCPY,DB_HOME_12201_WCPY=DB_  
HOME_12201_PATCHED_WCPY -targetnode node1 {authentication_option}
```

When you run the command, you move your active Oracle Grid Infrastructure from working copy `GI_HOME_12201_WCPY` to `GI_HOME_12201_PATCHED_WCPY`, Oracle RAC Database `db1` from `DB_HOME_12201_WCPY` to `DB_HOME_12201_PATCHED_WCPY`, and Oracle RAC Database `db2` from `DB_HOME_12102_WCPY` to `DB_HOME_12102_PATCHED_WCPY`.

Patching Oracle Database 12c Release 1 Without Downtime

This procedure explains how to patch Oracle Database 12c release 1 (12.1.0.2) with the latest patching without bringing down the database.

Before You Begin

You have an Oracle Database `db12102` that you want to patch to the latest patch level.

Ensure that the working copy `db12102_psu` based on the image `DB12102_PSU` contains the latest patches and is available.

Procedure

From the Fleet Patching and Provisioning Server, run one of the following commands as per your source and destination database:

1. To patch an Oracle Database home managed by Fleet Patching and Provisioning, and there exist working copies of the source and destination databases, run:

```
rhpctl move database -sourcewc db12102 -patchedwc db12102_psu
```

`db12102` is the source working copy of the database being patched

`db12102_psu` is the working copy of the Oracle Database software with patches applied, based on the image `DB12102_PSU`.

2. To patch an unmanaged Oracle Database home (source working copy does not exist because the Oracle home is not managed by Fleet Patching and Provisioning), run:

```
rhpctl move database -sourcehome /u01/app/orabase/product/12.1.0.2/  
dbhome_1  
-patchedwc db12102_psu -targetnode node1
```

`targetnode` specifies the node on which the database to be upgraded is running, because the source Oracle Database is on a 12.1.0.2 cluster.

`/u01/app/orabase/product/12.1.0.2/dbhome_1` is the path of the database being patched

`db12102_psu` is the working copy of the Oracle Database software with patches applied, based on the image `DB12102_PSU`.

Use the saved gold image for standardized patching of all your databases of release 12c release 1 to the same patch level.

3. If for some reason, you want to rollback the patches applied to a managed Oracle Database home, run:

```
rhpctl move database -sourcewc db12102_psu  
-patchedwc db12102 -ignorewcpatches
```

`db12102` is the working copy of the unpatched database to which you want to roll back.

db12102_psu is the working copy of the Oracle Database software with patches applied, based on the image DB12102_PSU.

For all Oracle Databases, you can also specify these additional options with the `move database` command:

- `-keepplacement`: For admin-managed Oracle RAC Databases (not Oracle RAC One Node Database), Fleet Patching and Provisioning retains the services on the same nodes after the move.
- `-disconnect`: Disconnects all sessions before stopping or relocating services.
- `-drain_timeout`: Specify the time, in seconds, allowed for resource draining to be completed for planned maintenance operations. During the draining period, all current client requests are processed, but new requests are not accepted. This option is available only with Oracle Database 12c release 2 (12.2) or later.
- `-stopoption`: Stops the database.
- `-nodatapatch`: Ensures `datapatch` is not run for databases you are moving.

Watch a video  [Video](#)

Upgrading to Oracle Database 12c Release 2

This procedure describes how to upgrade an Oracle database from Oracle Database 11g release 2 (11.2) to 12c release 2 with a single command, using Fleet Patching and Provisioning, both for managed and unmanaged Oracle homes.

Before you Begin

- To upgrade to Oracle Database 12c release 2 (12.2.0.1), your source database must be either Oracle Database 11g release 2 (11.2.0.3 or 11.2.0.4), or Oracle Database 12c release 1 (12.1.0.2).
- Oracle Grid Infrastructure on which the pre-upgrade database is running must be of the same release or later than the database release to which you are upgrading.
- The source Oracle home to be upgraded can be a managed working copy, that is an Oracle home provisioned using Fleet Patching and Provisioning, or an unmanaged home, that is, an Oracle home not provisioned using Fleet Patching and Provisioning. If you are upgrading an unmanaged Oracle home, provide the complete path of the database for upgrade.

Procedure to Upgrade Oracle Database using Fleet Patching and Provisioning

- From the Fleet Patching and Provisioning Server, run one of the following commands as per your source and destination database:
 1. To upgrade an Oracle home managed by Fleet Patching and Provisioning, and there exist working copies of the source and destination databases, run:

```
$ rhpctl upgrade database -dbname test_database -sourcewc db112  
-destwc db122  
  {authentication_option}
```

`test_database` is the name of the database being upgraded.

`db112` is the source working copy of the pre-upgrade database.

db122 is the working copy of the upgraded Oracle Database software.

2. To upgrade an unmanaged Oracle home (source working copy does not exist because the Oracle home is not managed by Fleet Patching and Provisioning), run:

```
$ rhpctl move database -sourcehome /u01/app/orabase/product/
11.2.0/dbhome_1
  -destwc db122 -targetnode node1 {authentication_option}
```

/u01/app/orabase/product/11.2.0/dbhome_1 is the path of the database being upgraded.

db122 is the working copy of the upgraded Oracle Database software.

targetnode specifies the node on which the database to be upgraded is running, because the source Oracle Database is on a 11.2.0.4 cluster.

The upgraded database is now managed by Fleet Patching and Provisioning. You can ensure that your database is patched to the latest level, using Fleet Patching and Provisioning.

Note:

During upgrade, if an error occurs, the procedure stops and allows you to fix the error. After fixing the error, you can resume the upgrade operation from where it last stopped.

Watch a video  [Video](#)

Related Topics

- [rhpctl upgrade database](#)
Upgrades a database to the version of the destination working copy.
- [rhpctl move database](#)
Moves one or more databases from a source working copy or any Oracle Database home to a patched working copy.

Adding a Node to a Cluster and Scaling an Oracle RAC Database to the Node

You can add a node to your two-node cluster by using Fleet Patching and Provisioning to add the node, and then extend an Oracle RAC database to the new node.

Before You Begin

In this procedure, Oracle Grid Infrastructure 12c release 2 (12.2.0.1) is running on the cluster. Working copy GI_HOME_12202_WCPY is the active Grid home on this cluster.

The Oracle RAC database home runs on the working copy DB_HOME_12202_WCPY.

Ensure that you have storage, network, and operating system requirements configured for the new node as stated in *Oracle Grid Infrastructure Installation Guide*.

Procedure

1. From the Fleet Patching and Provisioning Server, run the following command to add a node to the existing Oracle Grid Infrastructure working copy:

```
rhctl addnode gihome -workingcopy GI_HOME_12202_WCPY -newnodes  
n3:n3-vip {authentication_option}
```

The command extends the cluster by adding `node3`.

2. Add instances to the administrator-managed Oracle RAC database on the new node:

```
rhctl addnode database -workingcopy DB_HOME_12202_WCPY -dbname  
db321 -node n3 {authentication_option}
```

The command extends the database home on the `node3` and creates database `db321` on this node.

Related Topics

- [rhctl addnode gihome](#)
- [rhctl addnode database](#)

Adding Gold Images for Fleet Patching and Provisioning

Create gold images of software home and store them on the Fleet Patching and Provisioning Server, to use later to provision Oracle homes.

Before You Begin

The Oracle home to be used for creating the gold image can be on the Fleet Patching and Provisioning Server, or Fleet Patching and Provisioning Client, or any target machine that the Fleet Patching and Provisioning Server can communicate with.

Procedure

Create gold images of Oracle homes in any of the following ways and store them on the Fleet Patching and Provisioning server:

1. Import an image from an installed Oracle home on the Fleet Patching and Provisioning Server:

```
rhctl import image -image db12201 -path /share/software/122/dbhome  
-imagetype ORACLEDBSOFTWARE
```

The gold image of `imagetype` Oracle Database 12c release 2 software is created and stored on the Fleet Patching and Provisioning Server.

You can also create gold images of Oracle Grid Infrastructure or any other software by specifying `-imagetype` as `ORACLEGISOFTWARE`, `ORACLEGGSOFTWARE`, or `SOFTWARE` respectively.

2. Import an image from an installed Oracle home on a Fleet Patching and Provisioning Client by running the following command from the Fleet Patching and Provisioning Client:

```
rhpcctl import image -image db12201 -path /u01/app/dbusr/product/  
12.2.0/
```

The command creates and adds the image `db12201` based on the local Oracle home installed in the specified path.

**Note:**

You cannot directly use images as software homes. Use images to create working copies of software homes.

User Actions for Common Fleet Patching and Provisioning Tasks

You can use Fleet Patching and Provisioning user actions to perform many tasks, such as installing and configuring any type of software and running scripts.

Deploying a Web Server

The following procedure demonstrates automated deployment of Apache Web Server using Fleet Patching and Provisioning:

1. Create a script to install Apache Web server, as follows:
 - a. On the Fleet Patching and Provisioning Server, download and extract the Apache Web server installation kit.
 - b. Create the script to install, configure, and start the Apache Web server.
2. Register the script as a user action with Fleet Patching and Provisioning by running the following command on the Fleet Patching and Provisioning Server:

```
rhpcctl useraction -useraction apachestart  
-actionscript /user1/useractions/apacheinstall.sh  
-post -optype ADD_WORKINGCOPY -onerror ABORT
```

The preceding command adds the `apachestart` user action for the action script stored in the specified directory. As per the specified properties, the user action runs after the `ADD_WORKINGCOPY` operation and aborts if there is any error.

3. Create an image type and associate the user action with the image type, as follows:

```
rhpcctl add imagetype -imagetype apachetype -basetype SOFTWARE  
-useraction "apachestart"
```


The preceding command creates a new image type called `apachetype`, a derivative of the basic image type, `SOFTWARE`, with an associated user action `apachestart`.

4. Create a gold image of the image type, as follows:

```
rhpcctl import image -image apacheinstall -path /user1/  
apache2219_kit/  
-imagetype apachetype
```

The preceding command creates a gold image, `apacheinstall`, with the script for Apache Web server installation, in the specified path, based on the `imagetype` you created earlier.

To view the properties of this image, run the `rhpcctl query image -image apacheinstall` command.

5. Deploy a working copy of the gold image on the target, as follows:

```
rhpcctl add workingcopy -workingcopy apachecopy -image apacheinstall  
-path /user1/apacheinstallloc -sudouser user1  
-sudopath /usr/local/bin/sudo -node node1 -user user1  
-useractiondata "/user1/apachehome:1080:2.2.19"
```

Fleet Patching and Provisioning provisions the software to the target and runs the `apachestart` script specified in the user action. You can provide the Apache Web server configuration details such as port number with the `useractiondata` option. If the target is a Fleet Patching and Provisioning Client, then you need not specify `sudo` credentials.

Registering Multiple Scripts Using a Single User Action

Run multiple scripts as part of a user action plug-in by registering a wrapper script and bundled custom scripts. The wrapper script extracts the bundled scripts, which are copied under the directory of the wrapper script, and then runs those extracted scripts as necessary, similar to the following procedure:

1. The following command creates a user action called `ohadd_ua`, and associates a wrapper script, `wc_add.sh`, with a zip file containing other scripts:

```
rhpcctl add useraction -useraction ohadd_ua -actionscript  
/scratch/crsusr/wc_add.sh -actionfile /scratch/crsusr/pack.zip -pre  
-runscope  
ALLNODES -optype ADD_WORKINGCOPY
```

The wrapper script, `wc_add.sh`, extracts the `pack.zip` file into the script path, a temporary path to which the user action scripts are copied. The wrapper script can invoke any scripts contained in the file.

2. The following command creates an image type, `sw_ua`, for the `ohadd_ua` user action:

```
rhpcctl add imagetype -imagetype sw_ua -useractions ohadd_ua -  
basetype SOFTWARE
```

3. The following command creates an image called `swimgua` from the software specified in the path:

```
rhpcctl import image -image swimgua -path /tmp/custom_sw -imagetype  
sw_ua
```

4. The following command adds a working copy called `wcua` and runs the `wc_add.sh` script:

```
rhpcctl add workingcopy -workingcopy wcua -image swimgua -client  
targetcluster
```

A

Oracle Fleet Patching and Provisioning Control (RHPCTL) Command Reference

Use the Oracle Fleet Patching and Provisioning Control (RHPCTL) utility to manage Oracle Fleet Patching and Provisioning in your cluster.

This appendix contains reference information for Oracle Fleet Patching and Provisioning commands, including utility usage information and a comprehensive listing of the RHPCTL commands.

See Also:

Oracle Database REST API Reference for information about REST APIs for many common RHPCTL operations, including provisioning, patching, upgrading, and query operations.

RHPCTL Overview

RHPCTL is a command-line utility with which you perform Oracle Fleet Patching and Provisioning operations and manage Oracle Fleet Patching and Provisioning Servers and Clients. RHPCTL uses the following syntax:

```
rhpctl command object [parameters]
```

In RHPCTL syntax:

- *command* is a verb such as `add`, `delete`, or `query`
- *object* (also known as a noun) is the target or object on which RHPCTL performs the command, such as `client` or `image`.
- *parameters* extend the use of a preceding command combination to include additional parameters for the command. Specify parameters as `-keyword value`. If the *value* field contains a comma-delimited list, then do not use spaces between the items in the list.

You can use RHPCTL commands to perform several Oracle Fleet Patching and Provisioning operations, including:

- Oracle Fleet Patching and Provisioning Client operations, such as creating an Oracle Fleet Patching and Provisioning Client configuration.
- Role operations, such as adding and deleting roles, and granting and revoking roles for users.
- Site operations, such as obtaining configuration information for Oracle Fleet Patching and Provisioning Servers.
- Image operations, such as adding, deleting, and importing images.
- Image series operations, such as adding and deleting image series.

- Working copy operations, such as adding and deleting working copies.

Using RHPCTL Help

To see help for all RHPCTL commands, from the command line enter:

```
rhpcctl -help
```

To see the command syntax and a list of parameters for each RHPCTL command, from the command line enter:

```
rhpcctl command (or verb) object (or noun) -help
```

RHPCTL Command Reference

This section describes RHPCTL command usage information, and lists and describes RHPCTL commands.

Note:

A multitenant container database is the only supported architecture in Oracle Database 21c. While the documentation is being revised, legacy terminology may persist. In most cases, "database" and "non-CDB" refer to a CDB or PDB, depending on context. In some contexts, such as upgrades, "non-CDB" refers to a non-CDB from a previous release.

rhpcctl delete audit

Deletes the Fleet Patching and Provisioning audit records.

Syntax

```
rhpcctl delete audit [-to timestamp]
```

Usage Notes

Optionally, you can specify a date up to which audit records will be deleted, in the format *YYYY-MM-DD*. Otherwise, this command deletes all audit records.

rhpcctl modify audit

Modifies the maximum number of audit records to store.

Syntax

```
rhpcctl modify audit -maxrecord number
```

Usage Notes

Specify the maximum number of audit records to store.

rhpcctl query audit

Displays the Fleet Patching and Provisioning audit records.

Syntax

```
rhpcctl query audit [[[-operation {add | delete | modify | grant |
revoke | move | verify | discover
| upgrade | allow | disallow | deleteimage | insertimage | promote |
addnode | deletenode | register | unregister | export | import | query
| subscribe | unsubscribe}]
[-entity {client | role | audit | image | imagetype | useraction |
series | workingcopy | database | server | user | audit | imagetype |
useraction}]
| [-user user_name] [-client cluster_name] | [-from timestamp -to
timestamp]
| -before timestamp | -since timestamp | -first number | -last number]
| -record record_id | -config]
```

Parameters

Table A-1 rhpcctl query audit Command Parameters

Parameter	Description
-operation {add delete modify grant revoke move verify discover upgrade allow disallow deleteimage insertimage promote addnode deletenode register unregister export import query subscribe unsubscribe}	Specify the type of operation for which you want an audit query.
-entity {client role image series workingcopy database server user audit imagetype useraction}	Specify the entity for which you want an audit query.
-user <i>user_name</i>	Optionally, you can choose to run a query audit on a particular user who performed Fleet Patching and Provisioning operations.
-client <i>cluster_name</i>	Optionally, you can choose to run a query audit on a particular client cluster where Fleet Patching and Provisioning operations were performed.

Table A-1 (Cont.) rhpctl query audit Command Parameters

Parameter	Description
<code>-from timestamp -to timestamp</code>	Optionally, you can specify a time interval for which to run an audit query. Timestamps must be in the format <code>YYYY-MM-DD</code> .
<code>-before timestamp</code>	Optionally, you can specify a time before which to run an audit query. Timestamp must be in the format <code>YYYY-MM-DD</code> .
<code>-since timestamp</code>	Optionally, you can specify a time after which to run an audit query. Timestamp must be in the format <code>YYYY-MM-DD</code> .
<code>-first number</code>	Optionally, you can specify a number of the first audit records for a given time.
<code>-last number</code>	Optionally, you can specify a number of the last audit records for a given time.
<code>-record record_id</code>	Optionally, you can specify a particular audit record ID.
<code>-config</code>	You can choose this parameter to show the maximum record configuration.

rhpctl add client

Adds a Fleet Patching and Provisioning Client to the Fleet Patching and Provisioning Server configuration.

Syntax

```
rhpctl add client -client cluster_name [-toclientdata path] [-targetnode node_name
  {-sudouser sudo_user_name -sudopath sudo_binary_location | -root |
  -cred cred_name} | -auth plugin_name [-arg1 name1:value1...]]
  [-maproles role=user_name[,role=user_name[,...]]]
  [-version version]
```

Parameters

Table A-2 rhpctl add client Command Parameters

Parameter	Description
<code>-client client_name</code>	Specify the name of the cluster in which you want to create the client.
<code>-toclientdata path</code>	Optionally, you can specify the path to the XML file that is created by the Fleet Patching and Provisioning Server (specific to the client cluster), which contains the information the client needs to configure its connection to the server.
<code>-targetnode node_name</code>	Optionally, you can specify the name of a node in a remote cluster that has no Fleet Patching and Provisioning Client.

Table A-2 (Cont.) rhpctl add client Command Parameters

Parameter	Description
<code>-sudouser</code> <code>sudo_user_name</code>	If you choose to use the <code>-targetnode</code> parameter, then you must choose either <code>sudo</code> or <code>root</code> to access the remote node.
<code>-sudopath</code> <code>sudo_binary_location</code> <code> -root -cred</code> <code>cred_name</code>	If you choose <code>sudo</code> , then you must use the <code>-sudouser</code> parameter and specify a user name to run super-user operations, and a path to the location of the <code>sudo</code> binary. Optionally, you can choose to specify a credential name to associate the user and password credentials to access a remote node.
<code>-auth plugin_name</code> <code>[-arg1</code> <code>name1:value1...]</code>	Alternative to <code>-sudouser</code> , <code>-root</code> , or <code>-cred</code> , you can use <code>-auth</code> to specify an authentication plugin to access a remote node.
<code>-maproles</code> <code>role=user_name[,...]</code>	You can specify either built-in roles or roles that you have defined, and you can assign multiple users to each role. Use commas to separate multiple roles and users.
<code>-version version</code>	Optionally, you can specify the version of the credentials file format, such as 18.0.0.0.0.

 **Note:**

Starting with Oracle Grid Infrastructure 21c, the `-maproles` parameter is deprecated. This parameter can be desupported in a future release.

Usage Notes

- Only clusters running Oracle Grid Infrastructure 12c release 2 (12.2) or later can be configured and added as Fleet Patching and Provisioning Clients. Clusters running earlier versions of Oracle Grid Infrastructure, and servers running no Oracle Grid Infrastructure, can be managed directly by the Fleet Patching and Provisioning Server.
- You can only run this command on the Fleet Patching and Provisioning Server.

Examples

To add a client to the Fleet Patching and Provisioning Server:

```
$ rhpctl add client -client ClientCluster3 -toclientdata Grid_home/
RHPserver/info
```

rhpctl allow client

Enables a user or a role to perform an operation on an Oracle Fleet Patching and Provisioning client or remote cluster.

Syntax

```
rhpcctl allow client -client client_name
    {-user username [-cluster cluster_name] | -role role_name}
```

Parameters

Table A-3 rhpcctl allow client Command Parameters

Parameter	Description
-client <i>client_name</i>	Specify the name of the FPP client or remote cluster.
-user <i>username</i>	Specify the name of the operating system (OS) user
-cluster <i>cluster_name</i>	Optionally, you can specify the name of a cluster.
-role <i>role_name</i>	Specify the name of the role.

Usage Notes

- Specify the name of an Oracle Fleet Patching and Provisioning client or a remote cluster.
- Specify the OS user and optionally a name of a cluster, or the name of a role.
For a list of roles, refer to [rhpcctl add role](#)
- This command can only be run on an Oracle Fleet Patching and Provisioning server

Examples

Example A-1 Using rhpcctl allow client

```
$ rhpcctl add role -role SECURE_CLIENT_USER -hasRoles GH_CLIENT_ACCESS
$ rhpcctl disallow client -client secure_rhpc1 -role GH_CLIENT_ACCESS
$ rhpcctl allow client -client secure_rhpc1 -role SECURE_CLIENT_USER
$ rhpcctl grant role -role SECURE_CLIENT_USER -user secure_user1
```

rhpcctl delete client

Deletes a specific Fleet Patching and Provisioning Client from the configuration.

Syntax

```
rhpcctl delete client -client cluster_name [-force]
```


Usage Notes

- Specify the name of the client cluster that you want to delete from the configuration.
- You must stop the Fleet Patching and Provisioning Client before you run this command or use the `-force` option.

Example

To delete the Fleet Patching and Provisioning Client `ClientCluster3`:

```
$ rhpctl delete client -client ClientCluster3
```

rhpctl disallow client

Disables a user or a role to perform an operation on an Oracle Fleet Patching and Provisioning client or remote cluster.

Syntax

```
rhpctl disallow client -client client_name
    {-user username [-cluster cluster_name] | -role role_name}
```

Parameters

Table A-4 rhpctl disallow client Command Parameters

Parameter	Description
<code>-client <i>client_name</i></code>	Specify the name of the FPP client or remote cluster.
<code>-user <i>username</i></code>	Specify the name of the operating system (OS) user
<code>-cluster <i>cluster_name</i></code>	Optionally, you can specify the name of a cluster.
<code>-role <i>role_name</i></code>	Specify the name of the role.

Usage Notes

- Specify the name of an Oracle Fleet Patching and Provisioning client or a remote cluster.
- Specify the OS user and optionally a name of a cluster, or the name of a role. For a list of roles, refer to [rhpctl add role](#)
- This command can only be run on an Oracle Fleet Patching and Provisioning server

Examples

Example A-2 Using rhpctl disallow client

```
$ rhpctl add role -role SECURE_CLIENT_USER -hasRoles GH_CLIENT_ACCESS
$ rhpctl disallow client -client secure_rhpcl -role GH_CLIENT_ACCESS
$ rhpctl allow client -client secure_rhpcl -role SECURE_CLIENT_USER
$ rhpctl grant role -role SECURE_CLIENT_USER -user secure_user1
```

rhpctl discover client

Validates the input provided and discovers parameters on the given nodes, and generates a response file that you can use for configuring Oracle Clusterware. After completing this command, use [page A-12](#) to validate the response file and prepare the target nodes for Oracle Clusterware deployment.

Syntax

```
rhpctl discover client -image image_name -generatepath
response_file_path
  {-responsefile response_file_name | -clusternodes node_list -client
cluster_name
  -oraclehome oracle_home_path} {-root | -sudouser sudo_username
  -sudopath sudo_binary_path | -cred cred_name | -auth plugin_name
  [-arg1 name1:value1...] [-user gi_user_name]
  [-scan scan_name]
```

Parameters**Table A-5 rhpctl discover client Command Parameters**

Parameter	Description
-image <i>image_name</i>	Specify the name of the Oracle Grid Infrastructure Gold Image which the resulting response file will support.
-generatepath <i>response_file_path</i>	Specify a file path where the response file that RHPCTL generates will be copied. The RHPCTL command generates name of the response file and displays it while the command is running.
-responsefile <i>response_file_name</i>	If you have a partially complete response file and you want it to be completed with reference to the target nodes, then specify the response file name using this parameter. Note: The response file must include the node list, client name, and Oracle home path.
-clusternodes <i>node_list</i>	Specify a comma-delimited list of nodes on which you plan to provision Oracle Clusterware (using the resulting response file) in the following format: <i>node_name:node_vip[:node_role]</i> [, <i>node_name:node_vip[:node_role]</i> ...]
-client <i>cluster_name</i>	Specify the name of the target cluster to be probed.
-oraclehome <i>oracle_home_path</i>	Specify the location of the Oracle home.

Table A-5 (Cont.) rhpctl discover client Command Parameters

Parameter	Description
<code>-root</code> <code>-sudouser</code> <code>sudo_username</code> <code>-sudopath</code> <code>sudo_binary_path</code> <code>-cred cred_name</code> <code>-auth</code> <code>plugin_name [-arg1</code> <code>name1:value1...]</code>	You must choose either <code>sudo</code> or <code>root</code> to access the remote nodes. If you choose <code>sudo</code> , then you must specify a user name to run super-user operations, and a path to the location of the <code>sudo</code> binary. Optionally, you can choose to specify a credential name to associate the user and password credentials to access a remote node. Alternative to <code>-sudouser</code> , <code>-root</code> , or <code>-cred</code> , you can use <code>-auth</code> to specify an authentication plugin to access a remote node.
<code>-user gi_user_name</code>	Specify the name of the Oracle Grid Infrastructure installation user.
<code>-scan scan_name</code>	Specify the SCAN name.

rhpctl export client

Exports data from the repository on the Fleet Patching and Provisioning Server to a client data file.

Syntax

```
rhpctl export client -client cluster_name -clientdata file_path
```

Parameters

Table A-6 rhpctl export client Command Parameters

Parameter	Description
<code>-client <i>cluster_name</i></code>	Specify the name of the client cluster that you want to export.
<code>-clientdata</code> <code><i>file_path</i></code>	Specify the path to the location of the client data file.

Usage Notes

You can only run this command on the Fleet Patching and Provisioning Server.

Example

To export repository data from a Fleet Patching and Provisioning Client named `mjk9394` to a client data file, `/tmp/mjk9394.xml`:

```
$ rhpctl export client -client mjk9394 -clientdata /tmp/mjk9394.xml
```

rhpctl modify client

Modifies an Oracle Fleet Patching and Provisioning Client.

Syntax

```
rhctl modify client -client cluster_name [-enabled {TRUE | FALSE}]
  [-maproles role=user_name[+user_name...]]
  [,role=user_name[+user_name...],...] [-password]]
```

Parameters

Table A-7 rhctl modify client Command Parameters

Parameter	Description
-client <i>cluster_name</i>	Specify the name of the client cluster that you want to modify.
-enabled {TRUE FALSE}	Specify whether the client is enabled.
-maproles <i>role=user_name</i> [+ <i>user_name</i> ...] [,...]	You can modify either built-in roles or roles that you have defined, and you can assign multiple uses to each role. When you use the -maproles parameter, use a plus sign (+) to map more than one user to a specific role. Separate additional role/user pairs with commas.
-password	Optionally, you can recreate the Oracle Fleet Patching and Provisioning Client credentials.

 **Note:**

Starting with Oracle Grid Infrastructure 21c, the -maproles parameter is deprecated. This parameter can be desupported in a future release.

Example

To disable an Oracle Fleet Patching and Provisioning Client named RHPClient001:

```
$ rhctl modify client -client RHPClient001 -enabled FALSE
```

rhctl query client

Displays the configuration information of a specific Fleet Patching and Provisioning Client cluster.

Syntax

```
rhpctl query client [-client cluster_name[-detail [-node node_name] [-displayhtml]]]
                    [-rhpserver rhps_regex]
```

Parameters

Table A-8 rhpctl query client Command Parameters

Parameter	Description
-client <i>cluster_name</i>	Specify the name of the client cluster in which the Fleet Patching and Provisioning Client resides.
-detail	Generate cluster information (HTML) for the cluster.
-node <i>node_name</i>	Specify the name of a node in a remote cluster.
-displayhtml	Display the HTML cluster information for the cluster.
-rhpserver <i>rhps_regex</i>	Specify a regular expression to match the cluster name of the servers where the operation must be executed.

Usage Notes

Specify the name of the client cluster in which the Fleet Patching and Provisioning Client resides for which you want to display the configuration information.

When issuing a command for a peer server using the `-rhpserver` option, the user running the command must be an existing user of the peer server and the user must have a required role. To enable a user from a peer server to run commands on the local server, run the `rhpctl grant role` command to grant a required role to the peer server user and to specify the cluster name of the peer server to which the user belongs. For example:

```
$ rhpctl grant role -role role_name -user user_name -client cluster_name
```

To add multiple users, run the following command:

```
$ rhpctl grant role -client cluster_name -maproles
role=user_name[+user_name...][,role=user_name[+user_name...]]...
```

For information about granting roles with RHPCTL, refer to [rhpctl grant role](#)

Example

This command displays output similar to the following:

```
/rhpctl query client -client mbcluster-13
Site: mbcluster-13
Fleet Patching and Provisioning Client Version: 12.2.0.1.0
Enabled: true
Host from which RHPC last registered: rhpserver01.foo.com
Port number last registered by RHPC: 8896
```

```
RHP Enabled: true
Standalone: false
Managed: true
```

rhpcctl update client

Updates an image on the Fleet Patching and Provisioning Client.

Syntax

```
rhpcctl update client -image image_name {-targetnode node_name
| -batches '(node_name)'} -root
```

Parameters

Table A-9 rhpcctl update client Command Parameters

Parameter	Description
-image <i>image_name</i>	Specify the name of the image that you want to update.
-targetnode <i>node_name</i>	Specify the name of the node on which you want to update the Fleet Patching and Provisioning Client.
-batches ' <i>(node_name)</i> '	Alternative to specifying a target node, you can specify batches of nodes. Note: If you use this parameter for Oracle Database Appliance nodes, then run the command twice, in succession, specifying any one Oracle Database Appliance node for the first run, and another Oracle Database Appliance node for the second run.
-root	You must specify this parameter if you use either the -targetnode or -batches parameters.

Usage Notes

You can only run this command from a Fleet Patching and Provisioning Server.

Examples

The following example uses the -targetnode parameter:

```
$ rhpcctl update client -image ODA1 -targetnode rac07box1 -root
```

The two following examples use the -batches parameter:

```
$ rhpcctl update client -image ODA1 -batches '(rac07box1)' -root
$ rhpcctl update client -image ODA1 -batches '(rac07box2)' -root
```

rhpcctl verify client

Validates the input provided and creates or completes and verifies the values in a response file that you can use to configure Oracle Clusterware.

Syntax

```

rhpctl verify client -image image_name -responsefile response_file_name
  [-clusternodes node_list] {-root | -sudouser sudo_username -sudopath
  sudo_binary_path | -cred cred_name} | -auth plugin_name [-arg1
  name1:value1...]
  [-user gi_user_name] [-client cluster_name] [-scan scan_name]
  [-oraclehome oracle_home_path] [-ignorewarn] [-fixup [-setupSSH]]

```

Parameters

Table A-10 rhpctl verify client Command Parameters

Parameter	Description
-image <i>image_name</i>	Specify the name of the image.
-responsefile <i>response_file_name</i>	Specify a response file to be used to provision Oracle Grid Infrastructure.
-clusternodes <i>node_list</i>	Specify a comma-delimited list of nodes on which Oracle Clusterware will be provisioned in the following format: <i>node_name:node_vip[:node_role]</i> [, <i>node_name:node_vip[:node_role]</i> ...]
-root -sudouser <i>sudo_username</i> -sudopath <i>sudo_binary_path</i> -cred <i>cred_name</i> -auth <i>plugin_name</i> [-arg1 <i>name1:value1...</i>]	You must choose either <code>sudo</code> or <code>root</code> to access the remote nodes. If you choose <code>sudo</code> , then you must specify a user name to run super-user operations, and a path to the location of the <code>sudo</code> binary. Optionally, you can choose to specify a credential name to associate the user and password credentials to access a remote node. Alternative to <code>-sudouser</code> , <code>-root</code> , or <code>-cred</code> , you can use <code>-auth</code> to specify an authentication plugin to access a remote node.
-user <i>gi_user_name</i>	Specify the name of the Oracle Grid Infrastructure installation user.
-client <i>cluster_name</i>	Specify the name of the cluster you want to verify.
-scan <i>scan_name</i>	Specify the SCAN name.
-oraclehome <i>oracle_home_path</i>	Specify the location of the Oracle home.
-ignorewarn	Use this parameter to ignore warnings during validation.
-fixup [-setupSSH]	Use this parameter to run a fixup script, which automatically applies changes to the nodes to satisfy changes that CVU recommends. Optionally, you can use the <code>-setupSSH</code> parameter to set up passwordless SSH user equivalence on the remote nodes for the provisioning user.

rhpctl add credentials

Adds credentials to the Oracle Cluster Registry (OCR).

Syntax

```
rhpctl add credentials -cred cred_name {-root | -sudouser sudo_user_name
  -sudopath sudo_binary_location}
```

Parameters

Table A-11 rhpctl add credentials Command Parameters

Parameter	Description
-cred <i>cred_name</i>	Specify a credential name to associate the user and password credentials to access a remote node.
-root -sudouser <i>sudo_user_name</i> -sudopath <i>sudo_binary_location</i>	You must choose either to provide <i>root</i> access to access a remote node or a <i>sudo</i> user name and path to the <i>sudo</i> binary to perform super user operations.

Usage Notes

After you add credentials they can be used in the `-cred cred_name` parameter of other commands to avoid those commands prompting for a password.

rhpctl delete credentials

Deletes credentials from the Oracle Cluster Registry (OCR).

Syntax

```
rhpctl delete credentials -cred cred_name
```

Usage Notes

Specify only the name of the credentials you want to delete.

rhpctl add database

Creates a database using a specific working copy.

Syntax

```
rhpctl add database -workingcopy workingcopy_name
  { -gimr | -dbname unique_db_name {-node node_list |
    -serverpool pool_name [-pqpool pool_name |
    -newpqpool pool_name -pqcardinality cardinality] |
    -newpool pool_name -cardinality cardinality [-pqpool pool_name
    |
    -newpqpool pool_name -pqcardinality cardinality]}
  [-dbtype {RACONENODE | RAC | SINGLE}]
  [-dbtemplate file_path | image_name:relative_file_path]
  [-cdb] [-pdbName pdb_prefix [-numberOfPDBs pdb_count]]
  [{-sudouser user_name -sudopath sudo_binary_path |
```



```

-root | -cred cred_name |
-auth plugin_name [-arg1 name1:value1...]]]
[-targetnode node_name]
[-ignoreprereq]
[-fixup]]
[-datafileDestination datafileDestination_path]
[-useractiondata user_action_data]
[-eval] [-schedule {timer_value | NOW}]

```

Parameters

Table A-12 rhpctl add database Command Parameters

Parameter	Description
-workingcopy <i>workingcopy_name</i>	Specify the name of an existing working copy for the database that you want to add.
-gimr	Perform the operations required for a Grid Infrastructure Management Repository (GIMR) database
-dbname <i>unique_db_name</i>	Specify the unique name of the database (DB_UNIQUE_NAME without DB_DOMAIN) that you are adding.
-datafileDestination <i>datafileDestination_path</i>	Specify the data file destination location or the name of the Oracle Automatic Storage Management (Oracle ASM) disk group. Note: You cannot specify a disk group for Oracle Database versions before Oracle Database 11g release 2 (11.2).
-node <i>node_list</i>	Specify a node or comma-delimited list of several nodes on which to create the database.
-serverpool <i>server_pool_name</i>	Specify the name of an existing server pool.
-pqpool <i>server_pool_name</i>	Specify the name of an existing server pool. Note: This parameter is only applicable in an Oracle Flex Cluster environment and refers to server pools (either already defined, as in this case, or to be created when you use the -newpqpool parameter) running on non-Hub Nodes.
-newpqpool <i>server_pool_name</i>	Optionally, you can create a new server pool to be used for parallel queries. Specify a name for the new server pool. Note: This parameter is only applicable in an Oracle Flex Cluster environment because it refers to server pools running on non-Hub Nodes.
-pqcardinality <i>cardinality</i>	If you create a new server pool, then you must specify a cardinality value for the server pool. Note: This parameter is only applicable in an Oracle Flex Cluster environment.
-newpool <i>server_pool_name</i>	Optionally, you can create a new server pool. Specify a name for the new server pool.
-cardinality <i>cardinality</i>	If you create a new server pool, then you must specify a cardinality value for the server pool.
-dbtype {RACONENODE RAC SINGLE}	Specify whether the database is Oracle RAC One Node, Oracle RAC, or a nonclustered database.
-dbtemplate <i>file_path</i> <i>image_name:relative_file_path</i>	Specify the absolute file path to a database template or the relative path to the image home directory on a Fleet Patching and Provisioning Server.
-cdb	Optionally, use this parameter to create a database as a container database.

Table A-12 (Cont.) rhpctl add database Command Parameters

Parameter	Description
<code>-pdbName <i>pdb_prefix</i></code>	If you are creating one or more pluggable databases, then specify a pluggable database name prefix.
<code>-numberOfPDBs <i>pdb_count</i></code>	Specify the number of pluggable databases you want to create.
<code>-sudouser <i>user_name</i> -sudopath <i>sudo_binary_path</i> -root -cred <i>cred_name</i> - auth <i>plugin_name</i> [-arg1 <i>name1:value1...</i>]</code>	If you choose to use the <code>-targetnode</code> parameter, then you must choose either <code>sudo</code> or <code>root</code> to access the remote node. If you choose <code>sudo</code> , then you must specify a user name to run super-user operations, and a path to the location of the <code>sudo</code> binary. Optionally, you can choose to specify a credential name to associate the user and password credentials to access a remote node. Alternative to <code>-sudouser</code> , <code>-root</code> , or <code>-cred</code> , you can use <code>-auth</code> to specify an authentication plugin to access a remote node.
<code>-targetnode <i>node_name</i></code>	Optionally, you can specify the name of a node in a remote cluster that has no Oracle Fleet Patching and Provisioning Client.
<code>-ignoreprereq</code>	Ignore prerequisites.
<code>-fixup</code>	Execute a fixup script. This option is valid for Oracle Grid Infrastructure and database provisioning.
<code>-useractiondata <i>user_action_data</i></code>	Optionally, you can pass a value to the <code>useractiondata</code> parameter of the user action script.
<code>-schedule {<i>timer_value</i> NOW}</code>	Optionally, you can use this parameter to schedule a time to run this operation, in ISO-8601 format, as in the following example: 2018-07-25T19:13:17+05 If <code>NOW</code> is specified or the option is omitted, then the job is scheduled immediately.
<code>-eval</code>	Optionally, you can use this parameter to evaluate the impact of this command on the system without actually running the command.

Usage Notes

If you choose to use the `-schedule` parameter, then you must run this command on the Fleet Patching and Provisioning Server.

Authentication plugins enable the easy addition of authentication methods without changes in command line interfaces (CLIs). For information about authentication options, refer to [Authentication Options for Oracle Fleet Patching and Provisioning Operations](#).

Examples

To create a database on a working copy named `prodhome`:

```
$ rhpctl add database -workingcopy prodhome -dbname proddb -
datafileDestination /acfs/proddata -serverpool prodpool1 -dbtype RAC
```

 **Note:**

You can create multiple databases on a working copy.

rhpcctl addnode database

Adds instances to an administrator-managed Oracle RAC database.

Syntax

```
rhpcctl addnode database -workingcopy workingcopy_name
  -dbname unique_db_name -node node_list
  [-root | -cred cred_name | -sudouser sudo_user_name
  -sudopath sudo_binary_location |
  -auth plugin_name [-arg1 name1:value1 [-arg2 name2:value2 ...]]]
  [-useractiondata user_action_data] [-eval] [-schedule {timer_value |
  NOW}]
  [-revert]
```

Parameters

Table A-13 rhpcctl addnode database Command Parameters

Parameter	Description
-workingcopy <i>workingcopy_name</i>	Specify the name of a working copy.
-dbname <i>unique_db_name</i>	Specify the unique name of the database (DB_UNIQUE_NAME without DB_DOMAIN) that you are adding.
-node <i>node_list</i>	Specify a node or comma-delimited list of several nodes on which to create the database.
-root - cred <i>cred_name</i> -sudouser <i>sudo_user_name</i> -sudopath <i>sudo_binary_location</i> -auth <i>plugin_name</i> <i>plugin_args</i>	If you choose to use the -targetnode parameter, then you must choose either root, a credential name, sudo, or an authentication plugin to access the remote node. Choose -root to perform super user operations as root. Alternatively, you can choose either to specify a credential name to associate the user name and password credentials to access a remote node, to perform super user operations as a sudo user by specifying a sudo user name and the path to the sudo binary, or to use an authentication plugin to access the remote node.
-useractiondata <i>user_action_data</i>	Optionally, you can pass a value to the useractiondata parameter of the user action script.
-eval	Optionally, you can use this parameter to evaluate the impact of this command on the system without actually running the command.

Table A-13 (Cont.) rhpctl addnode database Command Parameters

Parameter	Description
<code>-schedule</code> <code>timer_value NOW</code>	Optionally, you can use this parameter to schedule a time to run this operation, in ISO-8601 format, as in the following example: 2018-07-25T19:13:17+05 If <code>NOW</code> is specified or the option is omitted, then the job is scheduled immediately.
<code>-revert</code>	On rerun, roll back the failed actions performed on the first run.

Usage Notes

- If the specified working copy is not installed on the nodes in the node list, then you must first run `rhpctl addnode workingcopy`.
- If the working copy is on a Fleet Patching and Provisioning Client or on the Fleet Patching and Provisioning Server, then credentials are not required. This is true whether you run the command on the Server or the Client. Credentials are required when you run the command on the Server and the working copy is on a target that is not a Fleet Patching and Provisioning Client.
- If you choose to use the `-schedule` parameter, then you must run this command on the Fleet Patching and Provisioning Server.

rhpctl addpdb database

Adds a pluggable database to an existing container database on a working copy. After you create a working copy of a gold image and provision that working copy to a target, and create a database as a multitenant container database, you can add a pluggable database to the container database on the working copy.

Syntax

```
rhpctl addpdb database -workingcopy workingcopy_name -cdbName cdb_name
  -pdbName new_pdb_name
  [-pdbDatafileDestination pdb_datafile_destination_path]
  [-pdbadminusername pdb_admin_user_name]
  [-dbcareponsefile responsefilename]
  [-root | -cred cred_name | -auth plugin_name [-arg1 name1:value1...]
  | -sudouser user_name -sudopath sudo_binary_path]
  [-targetnode node_name]
  [-useractiondata user_action_data]
  [-schedule {timer_value | NOW}]
```

Parameters

Table A-14 rhpctl addpdb database Command Parameters

Parameter	Description
<code>-workingcopy</code> <code>workingcopy_name</code>	Specify the name of an existing working copy for the pluggable database that you want to add.
<code>-cdbName</code> <code>cdb_name</code>	Specify the name of the multitenant container database to which you want to add the pluggable database.
<code>-pdbName</code> <code>new_pdb_name</code>	Specify a name for the pluggable database you are adding.
<code>-</code> <code>pdbDatafileDestinati</code> <code>on</code> <code>pdb_datafile_destina</code> <code>tion</code>	Optionally, you can specify the path to the data file destination location for the pluggable database.
<code>-pdbadminusername</code> <code>pdb_admin_user_name</code>	Optionally, you can specify the name of the PDB's local administrator.
<code>-dbcaresponsefile</code> <code>responsefilename</code>	Optionally, you can specify the name of the response file.
<code>-root</code> <code>-cred</code> <code>cred_name</code> <code>-auth</code> <code>plugin_name [-arg1</code> <code>name1:value1...]</code> <code>-sudouser</code> <code>user_name -sudopath</code> <code>sudo_binary_path</code>	<p>If you choose to use the <code>-targetnode</code> parameter, then you must choose either <code>sudo</code> or <code>root</code> to access the remote node.</p> <p>If you choose <code>sudo</code>, then you must specify a user name to run super-user operations, and a path to the location of the <code>sudo</code> binary.</p> <p>Optionally, you can choose to specify a credential name to associate the user and password credentials to access a remote node.</p> <p>Alternative to <code>-sudouser</code>, <code>-root</code>, or <code>-cred</code>, you can use <code>-auth</code> to specify an authentication plugin to access a remote node.</p>
<code>-targetnode</code> <code>node_name</code>	Optionally, you can specify the name of a node in the cluster on which you want to run this operation.
<code>-useractiondata</code> <code>user_action_data</code>	Optionally, you can pass a value to the <code>useractiondata</code> parameter of the user action script.
<code>-schedule</code> { <code>timer_value</code> <code>NOW</code> }	<p>Optionally, you can use this parameter to schedule a time to run this operation, in ISO-8601 format, as in the following example:</p> <p>2018-07-25T19:13:17+05</p> <p>If <code>NOW</code> is specified, then the job is scheduled immediately.</p>

Usage Notes

The working copy can be on Fleet Patching and Provisioning Server, a Fleet Patching and Provisioning Client, or a non-Fleet Patching and Provisioning Client target.

Example

The following example creates a pluggable database called `pdb183` on a container database called `raccdb183` on a working copy called `wc_db183`:

```
$ rhpctl addpdb database -workingcopy wc_db183 -cdbName raccdb183 -
pdbName pdb183
```

rhpctl deletepdb database

Deletes a pluggable database to an existing container database on a working copy.

Syntax

```
rhpctl deletepdb database -workingcopy workingcopy_name -cdbName
cdb_name
  -pdbName pdb_name
  [-root | -cred cred_name | -auth plugin_name [-arg1 name1:value1...]
  | -sudouser user_name -sudopath sudo_binary_path] [-targetnode
node_name]
  [-useractiondata user_action_data] [-schedule {timer_value | NOW}]
```

Parameters

Table A-15 rhpctl deletepdb database Command Parameters

Parameter	Description
<code>-workingcopy</code> <i>workingcopy_name</i>	Specify the name of an existing working copy for the pluggable database that you want to delete.
<code>-cdbName</code> <i>cdb_name</i>	Specify the name of the multitenant container database from which you want to delete the pluggable database.
<code>-pdbName</code> <i>pdb_name</i>	Specify the name of the pluggable database you want to delete.
<code>-root</code> <code>-cred</code> <i>cred_name</i> <code>-auth</code> <i>plugin_name</i> [-arg1 <i>name1:value1...</i>] <code>-sudouser</code> <i>user_name</i> - <code>sudopath</code> <i>sudo_binary_path</i>	<p>If you choose to use the <code>-targetnode</code> parameter, then you must choose either <code>sudo</code> or <code>root</code> to access the remote node.</p> <p>If you choose <code>sudo</code>, then you must specify a user name to run super-user operations, and a path to the location of the <code>sudo</code> binary.</p> <p>Optionally, you can choose to specify a credential name to associate the user and password credentials to access a remote node.</p> <p>Alternative to <code>-sudouser</code>, <code>-root</code>, or <code>-cred</code>, you can use <code>-auth</code> to specify an authentication plugin to access a remote node.</p>
<code>-targetnode</code> <i>node_name</i>	Optionally, you can specify the name of a node in the cluster on which you want to run this operation.
<code>-useractiondata</code> <i>user_action_data</i>	Optionally, you can pass a value to the <code>useractiondata</code> parameter of the user action script.

Table A-15 (Cont.) rhpctl deletepdb database Command Parameters

Parameter	Description
-schedule { <i>timer_value</i> NOW}	Optionally, you can use this parameter to schedule a time to run this operation, in ISO-8601 format, as in the following example: 2018-07-25T19:13:17+05 If NOW is specified, then the job is scheduled immediately.

Usage Notes

The working copy can be on Fleet Patching and Provisioning Server, a Fleet Patching and Provisioning Client, or a non-Fleet Patching and Provisioning Client target.

Examples

The following example deletes a pluggable database called `pdb183` from a container database called `raccdb183` on a working copy called `wc_db183`:

```
$ rhpctl deletepdb database -workingcopy wc_db183 -cdbName raccdb183
-pdbName pdb183
```

rhpctl delete database

Deletes a database that was created on a working copy.

Note:

If the database is hosted on a working copy that is on the Oracle Fleet Patching and Provisioning Server or on an Oracle Fleet Patching and Provisioning Client, then credentials are not required. This is true whether you run the command on the Server or the Client. Credentials are required when you run the command on the Server and the working copy is on a target that is not an Oracle Fleet Patching and Provisioning Client.

Syntax

```
rhpctl delete database -workingcopy workingcopy_name -dbname
unique_db_name
{-sudouser sudo_user_name -sudopath sudo_binary_path |
-root | -cred cred_name |
-auth plugin_name [-arg1 name1:value1...]}
[-targetnode node_name]
[-useractiondata user_action_data]
[-schedule {timer_value | NOW}]
```

Parameters

Table A-16 rhpctl delete database Command Parameters

Parameter	Description
<code>-workingcopy</code> <code>workingcopy_name</code>	Specify a name for the working copy for the database that you want to delete.
<code>-dbname</code> <code>unique_db_name</code>	Specify the unique name of the database (DB_UNIQUE_NAME without DB_DOMAIN) that you are deleting.
<code>-sudouser user_name</code> <code>-sudopath</code> <code>sudo_binary_path</code> <code>-root</code> <code>-cred</code> <code>cred_name</code> <code>-auth</code> <code>plugin_name</code> [-arg1 <code>name1:value1...</code>]	<p>If you choose to use the <code>-targetnode</code> parameter, then you must choose either <code>sudo</code> or <code>root</code> to access the remote node.</p> <p>If you choose <code>sudo</code>, then you must specify a user name to run super-user operations, and a path to the location of the <code>sudo</code> binary.</p> <p>Optionally, you can choose to specify a credential name to associate the user and password credentials to access a remote node.</p> <p>Alternative to <code>-sudouser</code>, <code>-root</code>, or <code>-cred</code>, you can use <code>-auth</code> to specify an authentication plugin to access a remote node.</p>
<code>-targetnode</code> <code>node_name</code>	Optionally, you can specify the name of a node in a remote cluster that has no Oracle Fleet Patching and Provisioning Client.
<code>-useractiondata</code> <code>user_action_data</code>	Optionally, you can pass a value to the <code>useractiondata</code> parameter of the user action script.
<code>-schedule</code> { <code>timer_value</code> NOW}	<p>Optionally, you can use this parameter to schedule a time to run this operation, in ISO-8601 format, as in the following example:</p> <p>2018-07-25T19:13:17+05</p> <p>If NOW is specified, then the job is scheduled immediately.</p>

rhpctl deletenode database

Deletes an instance, which contracts an administrator-managed Oracle RAC database.

Syntax

```
rhpctl deletenode database -workingcopy working_copy_name -dbname
unique_db_name
-node node_list {-root | -sudouser sudo_username -sudopath
sudo_binary_path
| -cred cred_name | -auth plugin_name [-arg1 name1:value1...]} [-
force]
[-failover] [-drain_timeout timeout] [-stopoption stop_option]
[-useractiondata user_action_data] [-schedule {timer_value | NOW}] [-
eval]
```


Parameters

Table A-17 rhpctl deletenode database Command Parameters

Parameter	Description
<code>-workingcopy</code> <code>working_copy_name</code>	Specify the name of a working copy.
<code>-dbname</code> <code>unique_db_name</code>	Specify the unique name of the database (DB_UNIQUE_NAME without DB_DOMAIN) that you are deleting.
<code>-node node_list</code>	Specify a node or comma-delimited list of several nodes from which to delete the database instance.
<code>-root</code> <code>-sudouser</code> <code>sudo_username</code> <code>-sudopath</code> <code>sudo_binary_path</code> <code>-cred cred_name</code> <code>-auth</code> <code>plugin_name [-arg1</code> <code>name1:value1...]</code>	Choose either <code>sudo</code> or <code>root</code> to access the remote nodes. If you choose <code>sudo</code> , then you must specify a user name to run super-user operations, and a path to the location of the <code>sudo</code> binary. Optionally, you can choose to specify a credential name to associate the user and password credentials to access a remote node. Alternative to <code>-sudouser</code> , <code>-root</code> , or <code>-cred</code> , you can use <code>-auth</code> to specify an authentication plugin to access a remote node.
<code>-force</code>	Use <code>-force</code> to remove the instance after forcibly stopping the instance.
<code>-failover</code>	Optionally, you can use this parameter to attempt to have services running on the instance that want to delete fail over to another instance.
<code>-drain_timeout</code> <code>timeout</code>	Optionally, you can use <code>-drain_timeout</code> to specify the time, in seconds, allowed for resource draining to be completed. Accepted values are an empty string (""), 0, or any positive integer. The default value is an empty string, which means that this parameter is not set. If it is set to 0, then draining occurs, immediately. The draining period is intended for planned maintenance operations. During the draining period, all current client requests are processed, but new requests are not accepted.
<code>-stopoption</code> <code>stop_option</code>	Optionally, you can specify a stop option for the database. Options include: ABORT, IMMEDIATE, NORMAL, TRANSACTIONAL, and TRANSACTIONAL_LOCAL.
<code>-useractiondata</code> <code>user_action_data</code>	Optionally, you can pass a value to the <code>useractiondata</code> parameter of the user action script.
<code>-schedule</code> (<code>timer_value</code> NOW}	Optionally, you can use this parameter to schedule a time to run this operation, in ISO-8601 format, as in the following example: 2018-07-25T19:13:17+05 If NOW is specified, then the job is scheduled immediately.
<code>-eval</code>	Optionally, you can use this parameter to evaluate the impact of this command on the system without actually running the command.

Usage Notes

- If the working copy is on a Fleet Patching and Provisioning Client or on the Fleet Patching and Provisioning Server, then credentials are not required. This is true whether you run the command on the Server or the Client. Credentials are required when you run the command on the Server and the working copy is on a target that is not a Fleet Patching and Provisioning Client.
- If you choose to use the `-schedule` parameter, then you must run this command on the Fleet Patching and Provisioning Server.

rhpctl move database

Moves one or more databases from a source working copy or any Oracle Database home to a patched working copy.

Syntax

```
rhpctl move database -patchedwc workingcopy_name
  {{-sourcewc workingcopy_name |
   -sourcehome Oracle_home_path [-oraclebase Oracle_base_path]
  [-client cluster_name]}
  [-dbname db_name_list | -excludedblist db_name_list]
  [-nonrolling [-skipprereq] | -forcerolling | -batches list_of_batches | -smartmove
  [-saf availability] [-separate]]
  [-eval]
  [-ignoremissingpatches patch_name1 [,patch_name2...]]
  [-ignorewcpatches] [-keepplacement]
  [-disconnect [-noreplay]] [-drain_timeout time] [-stopoption stop_option]
  [-nodatapatch] [-targetnode node_name] [-notify [-cc user_list]] |
  -continue [-skip] | -revert | -abort}
  [-root | -cred cred_name | -sudouser sudo_user_name
  -sudopath sudo_binary_location |
  -auth plugin_name [-arg1 name1:value1 [-arg2 name2:value2 ...]]]
  [schedule {timer_value| NOW}]
  [-useractiondata user_action_data]
  [-dbsinparallel <number_of_instances>] [-raconetimeout <timeout>]
```

Parameters

Table A-18 rhpctl move database Command Parameters

Parameter	Description
<code>-patchedwc</code> <i>workingcopy_name</i>	Specify the name of the working copy to where you want to move the database.
<code>-sourcewc</code> <i>workingcopy_name</i>	Specify the name of the working copy from which the database is to be moved.
<code>-sourcehome</code> <i>Oracle_home_path</i>	Alternatively, you can specify the source Oracle home path.
<code>-oraclebase</code> <i>Oracle_base_path</i>	Specify the <code>ORACLE_BASE</code> path for provisioning the Oracle database home (required only for <code>ORACLEEDBSOFTWARE</code> image type).

Table A-18 (Cont.) rhpctl move database Command Parameters

Parameter	Description
<code>-client cluster_name</code>	Specify the name of the client cluster.
<code>-dbname db_name_list</code>	Specify the unique names of the databases (DB_UNIQUE_NAME without DB_DOMAIN) that you want to move to the patched working copy. Note: If you are moving a non-clustered (single-instance) database, then, for the value of the <code>-dbname</code> parameter, you must specify the <i>SID</i> of the database instead of the database name.
<code>-excludedblist db_name_list</code>	Alternative to using the <code>-dbname</code> parameter, you can use the <code>-excludedblist</code> parameter to patch all databases except specific databases.
<code>-nonrolling [-skipprereq] -forcerolling -batches list_of_batches -smartmove [-saf availability] [-separate]</code>	Optionally, you can choose one of the three following methods to move a database: <ul style="list-style-type: none"> Use the <code>-nonrolling</code> parameter to move the database in a non-rolling mode. By default, databases move in a rolling mode. Use the <code>-skipprereq</code> option to skip the prerequisite checks and start the database in upgrade mode for patching. Use the <code>-forcerolling</code> parameter to force the Oracle home to move in rolling mode. Use the <code>-batches</code> parameter to specify a comma-delimited list of batches of nodes (where each batch is a comma-delimited list of node names enclosed in parentheses) enclosed in double quotation marks (") in the format: "(nA,nB,...),(...,nY,nZ)". Alternatively, use the <code>-smartmove</code> parameter. Use the <code>-saf availability</code> parameter to specify a service availability factor, which is the minimum percentage of instances on which a service must remain running during the move. Use the <code>-separate</code> parameter to process batches separately. When you use this parameter, the <code>move</code> command returns after each batch. The move operation for the first batch must specify the source home and other parameters that apply to all batches (such as <code>-nonrolling</code> and <code>-keepplacement</code>). Control subsequent batches using the <code>-continue</code> , <code>-skip</code> , and <code>-abort</code> parameters.
<code>-eval</code>	Use the <code>-eval</code> parameter to print auto-generated batches of nodes and sequence of moves without actually performing the move operation.
<code>-ignoremissingpatches patch_name1 [,patch_name2...]</code>	Perform the move and/or upgrade even though the specified patches, which are present in the source path or working copy, may be missing from the destination path or working copy.
<code>-ignorewcpatches</code>	Optionally, you can use this parameter to ignore if a patched working copy is missing some patches which are present in the source path or working copy.
<code>-keepplacement</code>	Use this parameter to ensure that services of administrator-managed Oracle RAC or Oracle RAC One Node databases are running on the same instances before and after the move operation.
<code>-disconnect [-noreplay]</code>	Optionally, use the <code>-disconnect</code> parameter to disconnect all sessions before stopping or relocating services. If you choose to use <code>-disconnect</code> , then you can choose to use the <code>-noreplay</code> parameter to disable session replay during disconnection.

Table A-18 (Cont.) rhpctl move database Command Parameters

Parameter	Description
<code>-drain_timeout timeout</code>	Specify the time, in seconds, allowed for resource draining to be completed. Accepted values are an empty string (""), 0, or any positive integer. The default value is an empty string, which means that this parameter is not set. If it is set to 0, then draining occurs, immediately. The draining period is intended for planned maintenance operations. During the draining period, all current client requests are processed, but new requests are not accepted.
<code>-stopoption stop_option</code>	Optionally, you can specify a stop option for the database. Options include: ABORT, IMMEDIATE, NORMAL, TRANSACTIONAL, and TRANSACTIONAL_LOCAL.
<code>-nodatapatch</code>	Use this parameter to indicate not to run datapatch for databases you are moving.
<code>-targetnode node_name</code>	Optionally, you can specify the name of a node in a remote cluster that has no Fleet Patching and Provisioning Client.
<code>-notify [-cc user_list]</code>	Optionally, you can supply a list of users to whom email notifications of the move will be sent, in addition to the owner of the working copy.
<code>-continue [-skip]</code>	If a batch-mode rhpctl move database command fails at any point, then, after correcting the cause of the error, you can rerun the command with the <code>-continue</code> parameter to attempt to patch the failed batch. If you want to skip the failed batch and continue with the next batch, use the <code>-continue</code> and <code>-skip</code> parameters together. If you attempt to skip over the last batch, then the move operation is terminated.
<code>-revert</code>	If a batch-mode or non-batch-mode rhpctl move database command fails, then you can rerun the command with the <code>-revert</code> parameter to undo the changes that have been made, and return the configuration to its initial state.
<code>-abort</code>	If a batch-mode or non-batch-mode rhpctl move database command fails, then you can rerun the command with the <code>-abort</code> parameter to terminate the patching process and leave the cluster in its current state.
<code>-root -cred cred_name -sudouser sudo_user_name -sudopath sudo_binary_location -auth plugin_name plugin_args</code>	If you choose to use the <code>-targetnode</code> parameter, then you must choose either <code>root</code> , a credential name, <code>sudo</code> , or an authentication plugin to access the remote node. Choose <code>-root</code> to perform super user operations as <code>root</code> . Alternatively, you can choose either to specify a credential name to associate the user name and password credentials to access a remote node, to perform super user operations as a <code>sudo</code> user by specifying a <code>sudo</code> user name and the path to the <code>sudo</code> binary, or to use an authentication plugin to access the remote node.
<code>-useractiondata user_action_data</code>	Optionally, you can pass a value to the <code>useractiondata</code> parameter of the user action script.
<code>-schedule {timer_value NOW}</code>	Optionally, you can use this parameter to schedule a time to run this operation, in ISO-8601 format. For example: 2018-07-25T19:13:17+05 If <code>NOW</code> is specified, then the job is scheduled immediately.
<code>-dbsinparallel number_of_instances</code>	Number of database instances that can be started in parallel on a given node.
<code>-raconetimeout timeout</code>	RAC One Node database relocation timeout in minutes.

Usage Notes

- You can obtain context sensitive help for specific use cases for the `rhpcctl move database` command, as follows:

```
$ rhpcctl move database -help [EXISTING_PATCHEDWC | NEW_PATCHEDWC |
SRCHOME
| SINGLEINSTANCEDB | ROLLING | NONROLLING | BATCHES | SMARTMOVE]
```

- If you choose to use the `-schedule` parameter, then you must run this command on the Fleet Patching and Provisioning Server.

Examples

To move all the databases running from one working copy to another in a rolling fashion:

```
$ rhpcctl move database -sourcewc prodHomeV1 -patchedwc prodHomeV2 -
client prodcluster
```

In the preceding example, the patched working copy, `prodHomeV2`, must exist.

To move all databases running on a non-managed Oracle home at `/u01/app/product/12.1.0/dbhome` to a working copy named `myDB12Home1`:

```
$ rhpcctl move database -sourcehome /u01/app/product/12.1.0/dbhome -
oraclebase /u01/app/product/12.1.0/obase -patchedwc myDB12Home1
```

To move a database named `SampleDB` from a working copy named `myDB12Home1` to a working copy named `myDB12Home1patched` (any other databases running on `myDB12Home1` are not affected by this move):

```
$ rhpcctl move database -sourcewc myDB12Home1 -patchedwc
myDB12Home1patched -dbname SampleDB
```

To move all databases running on a working copy named `myDB12Home1` to a working copy named `myDB12Home1patched`:

```
$ rhpcctl move database -sourcewc myDB12Home1 -patchedwc
myDB12Home1patched
```

To move a non-clustered (single-instance) database with a SID of `SID101` running on a patched working copy named `myDB12Home1patched`:

```
$ rhpcctl move database -patchedwc myDB12Home1patched -sourcehome
/u01/app/oracle/product/12.2.0/db_1 -targetnode vm02 -dbname SID101
-sudouser oracle -sudopath /usr/bin/sudo
```

The preceding examples are the basic form of the command. You can also move groups of databases in batches. The batch operations also support management of session connections and recovery options.

rhpcctl movepdb database

Moves specified pluggable databases from the source multitenant container database to the destination multitenant container database.

Syntax

```
rhpcctl movepdb database -sourcecdb source_cdb_name -destcdb
destination_cdb_name
    {-pdbname pdb_name_list | -excludepdblist pdb_name_list}
    [-root | -cred cred_name | -sudouser sudo_user_name
    -sudopath sudo_binary_location |
    -auth plugin_name [-arg1 name1:value1
    [-arg2 name2:value2 ...]]] [-client client_name | -targetnode
node_name]
    [-useractiondata user_action_data] [-schedule {timer_value | NOW}]
```

Parameters

Table A-19 rhpcctl movepdb database Command Parameters

Parameter	Description
-sourcecdb <i>source_cdb_name</i>	Specify the name of the Oracle Multitenant container database from which you want to move the pluggable database.
-destcdb <i>destination_cdb_name</i>	Specify the name of the multitenant container database to which you want to move the pluggable database.
-pdbname <i>pdb_name_list</i>	Specify a comma-separated list of names of pluggable databases that you want to move.
-excludepdblist <i>pdb_name_list</i>	Specify a list of pluggable databases that you want to excluded from the move operation.
-root -cred <i>cred_name</i> -sudouser <i>sudo_user_name</i> -sudopath <i>sudo_binary_location</i> -auth <i>plugin_name</i> <i>plugin_args</i>	If you choose to use the -targetnode parameter, then you must choose either root, a credential name, sudo, or an authentication plugin to access the remote node. Choose -root to perform super user operations as root. Alternatively, you can choose either to specify a credential name to associate the user name and password credentials to access a remote node, to perform super user operations as a sudo user by specifying a sudo user name and the path to the sudo binary, or to use an authentication plugin to access the remote node.
-client <i>client_name</i> -targetnode <i>node_name</i>	Optionally, you can specify either the name of the client cluster or the node on which the operation is to be run.
-useractiondata <i>user_action_data</i>	Optionally, you can pass a value to the useractiondata parameter of the user action script.

Table A-19 (Cont.) rhpctl movepdb database Command Parameters

Parameter	Description
<code>-schedule {<i>timer_value</i> NOW}</code>	<p>Optionally, you can use this parameter to schedule a time to run this operation, in ISO-8601 format, as in the following example:</p> <pre>2019-01-07T19:13:17+05</pre> <p>You can specify NOW to schedule the operation immediately.</p>

Usage Notes

- The source and destination container databases can be running in a provisioned database working copy. The working copy can be on the Oracle Fleet Patching and Provisioning Server, an Oracle Fleet Patching and Provisioning Client, or a non-Fleet Patching and Provisioning Client target, which is a target without an Oracle Fleet Patching and Provisioning Client configured and running. The destination container database can be at a higher patch level, which facilitates patching of a pluggable database to a higher patch level.
- You can only use this command if both the source and destination container databases are on the same node.
- This command does not currently support for Oracle RAC databases.

Examples

To move a pluggable database from a source container database to a destination container database:

```
rhpctl movepdb database -sourcecdb srccdb -pdbname pdb1,pdb2,pdb3 -
destcdb dstcdb
```

rhpctl upgrade database

Upgrades a database to the version of the destination working copy.

Syntax

```
rhpctl upgrade database [-sourcewc source_workingcopy_name | -
sourcehome oracle_home_path
  [-oraclebase Oracle_base_path] [{-client cluster_name | -targetnode
node_name}]]
  [-root | -cred cred_name | -sudouser sudo_username -sudopath
path_to_sudo_binary
  | -auth plugin_name [-arg1 name1:value1 [-arg2 name2:value2 ...]]]
  -destwc destination_workingcopy_name [-image image_name [-path
where_path]]
  -dbname unique_db_name [-useractiondata user_action_data] [-eval [-
preupg]
  [-schedule {timer_value | NOW}]
```

```
[-ignoremissingpatches patch_name1[,patch_name2...]  
[-dbuaargs dbua_arguments]  
[-autoupg [-upgtimezone { YES | NO }] [-runutlrp { YES | NO }]  
[-fra db_recovery_file_dest] -ignoregroupcheck ]  
[-drain_timeout session_drain_time] [-abort] [-revert]
```

Parameters

Table A-20 rhpctl upgrade database Command Parameters

Parameter	Description
-sourcewc <i>source_workingcopy_name</i>	Specify the name of the source working copy from which you want to upgrade the database.
-sourcehome <i>oracle_home_path</i>	Alternative to specifying the name of the source working copy, you can specify the path to the source Oracle home.
-oraclebase <i>oraclebase_path</i>	If you use the -sourcehome parameter, then you can, optionally, specify a different ORACLE_BASE from the source Home.
-client <i>cluster_name</i> - <i>targetnode node_name</i>	Specify either the name of the client cluster or the name of a node in a remote cluster with no Fleet Patching and Provisioning Client on which to provision a working copy.
-root -cred <i>cred_name</i> -sudouser <i>sudo_user_name</i> -sudopath <i>sudo_binary_location</i> -auth <i>plugin_name</i> <i>plugin_args</i>	If you choose to use the -targetnode parameter, then you must choose either root, a credential name, sudo, or an authentication plugin to access the remote node. Choose -root to perform super user operations as root. Alternatively, you can choose either to specify a credential name to associate the user name and password credentials to access a remote node, to perform super user operations as a sudo user by specifying a sudo user name and the path to the sudo binary, or to use an authentication plugin to access the remote node.
-destwc <i>destination_workingcopy_name</i> [-image <i>image_name</i> [-path <i>where_path</i>]]	Specify the name of the destination working copy to which the database is to be upgraded. If the destination working copy does not exist, then specify the gold image from which to create it, and optionally, the path to where to provision the working copy.
-dbname <i>unique_db_name</i>	Specify the name of the database you are upgrading.
-useractiondata <i>user_action_data</i>	Optionally, you can pass a value to the useractiondata parameter of the user action script.
-eval	Optionally, you can use this parameter to evaluate the impact of this command on the system without actually running the command.
-schedule { <i>timer_value</i> NOW }	Optionally, you can use this parameter to schedule a time to run this operation, in ISO-8601 format, as in the following example: 2018-07-25T19:13:17+05 If NOW is specified, then the job is scheduled immediately.
-ignoremissingpatches	Executes the move and/or upgrade although the specified patches, which are present in the source path or working copy, could be missing from the destination path or working copy.
-dbuaargs <i>dbua_arguments</i>	Species a double-quoted string containing optional arguments for DBUA.
-autoupg	Executes the upgrade database operation using the AutoUpgrade toolkit.
-upgtimezone { YES NO }	Enables or disables time zone upgrade as part of the AutoUpgrade process. Default is YES.
-runutlrp { YES NO }	Enables or disables the recompilation of invalid objects as part of the AutoUpgrade process. Default is YES.

Table A-20 (Cont.) rhpctl upgrade database Command Parameters

Parameter	Description
<code>-fra</code> <code>db_recovery_file_dest</code>	Specifies the location of the flash recovery area.
<code>-ignoregroupcheck</code>	Skips the group check except for OSDBA and OSASM during the upgrade database process.
<code>-drain_timeout</code> <code>session_drain_time</code>	Specifies the service drain timeout in seconds.
<code>-abort</code>	Terminate the ongoing upgrade operation.
<code>-revert</code>	Use this parameter to revert the failed upgrade of Oracle Database.

Usage Notes

If you choose to use the `-schedule` parameter, then you must run this command on the Fleet Patching and Provisioning Server.

Example

The following example upgrades a database, `testy`, from Oracle Database 11g, which is on working copy `db112mbc143` to Oracle Database 12c, which is on working copy `db12102mbc143`, both of which reside on the remote node `bposvr141`:

```
$ rhpctl upgrade database -dbname testy -sourcewc db112mbc143 -destwc
db12102mbc143 -root -targetnode bposvr141
```

rhpctl zdtupgrade database

The Zero Downtime Upgrade command `rhpctl zdtupgrade database` enables zero downtime database upgrades for Oracle RAC and Oracle RAC One Node Oracle Database instances.

Syntax

```
rhpctl zdtupgrade database -dbname unique_db_name -destwc
destination_workingcopy_name
  [converttopdb -cdbname cdb_name
   [-pdbname pdb_name]]
  [-sourcewc source_workingcopy_name | -sourcehome oracle_home_path]
  -ggsrwc golden_gate_source_workingcopy_name
  -ggdstwc golden_gate_dest_workingcopy_name
  [-clonedatadg diskgroup_name
   [-cloneredodg diskgroup_name]
   [-clonerecodg diskgroup_name]]
  [clonedataafs acfs_mountpoint
   [-cloneredofs acfs_mountpoint]
   [-clonerecofs acfs_mountpoint]]
  [-targetnode node_name
   {-root |
    -cred credential_name|
    -sudouser sudouser name -sudopath sudo_binary_location}
```

```

    -auth plugin_name
        [arg1 name1:value1
          [arg2 name2:value2. . . ]]]]
[-eval]
[-ignoreprereq]
[-useractiondata user_action_data]
[-dbuaargs dbua_arguments]

```

Parameters

Table A-21 rhpctl zdtupgrade database Command Parameters

Parameter	Description
-dbname <i>unique_db_name</i>	Specify the unique name of the database that you want to upgrade.
-converttopdb - cdbname <i>cdbname</i> - pdbname <i>pdb_name</i>	<p>(Optional) Specifies that you want to convert a non-container (non-CDB) Oracle Database to a pluggable database (PDB) during the upgrade.</p> <p>If you select this option, then provide the following arguments:</p> <ul style="list-style-type: none"> -cdbname <i>cdb_name</i>, which defines the name of the existing container database (CDB) on which you want to place the PDB -pdbname <i>pdb_name</i>, which defines the name of the PDB that you want to plug in to the CDB. <p>After the non-CDB source database is upgraded on the target node, if you specify -converttopdb, and provide the existing CDB's name, then Zero Downtime Upgrade performs the conversion.</p>
-destwc <i>destination_workingc opy_name</i>	Specifies the name of the destination working copy to which the database is to be upgraded.
-sourcewc <i>source_workingcopy_n ame</i>	(Optional) You can specify the name of the source working copy from which you want to upgrade the database.
-sourcehome <i>oracle_home_path</i>	Alternative to specifying the name of the source working copy, you can specify the path to the source Oracle home.
-ggsrwc <i>golden_gate_source_w orkingcopy_name</i>	Specify the name of the Oracle GoldenGate source working copy.
-ggdstwc <i>golden_gate_dest_wor kingcopy_name</i>	Specify the name of the Oracle GoldenGate destination working copy.
-clonedatadg <i>diskgroup_name</i>	(Optional) You can specify the name of an Oracle ASM disk group to use as a data file location for the cloned database.
-cloneredodg <i>diskgroup_name</i>	(Optional) You can specify the name of an Oracle ASM disk group to use as a redo log location for the cloned database.
-clonerecodg <i>diskgroup_name</i>	(Optional) You can specify the name of an Oracle ASM disk group to use as a recovery area for the cloned database.
clonedatafs <i>acfs_mountpoint</i>	(Optional) You can specify the mount point of an Oracle Automatic Storage Management Cluster File System (Oracle ACFS) to use as a data file location for the cloned database.

Table A-21 (Cont.) rhpctl zdtupgrade database Command Parameters

Parameter	Description
<code>-cloneredofs</code> <code>acfs_mountpoint</code>	(Optional) You can specify the name of an Oracle ACFS file system to use as a redo log location for the clone database.
<code>-clonerecofs</code> <code>acfs_mountpoint</code>	(Optional) You can specify the name of an Oracle ACFS file system to use as a recovery area for the clone database.
<code>-rmanlocation</code> <code>backup_location</code>	(Optional) You can specify the source RMAN backup location.
<code>-sourcename</code> <code>node_name</code>	(Optional) You can specify the name of a source node in a remote cluster with no Fleet Patching and Provisioning Client on which to provision a working copy, where the source database is running. If you choose to use the <code>-sourcename</code> parameter, then you must choose either <code>root</code> , a credential name, <code>sudo</code> , or an authentication plugin to access the remote node. Choose <code>-root</code> to perform super user operations as <code>root</code> . Alternatively, you can choose either to specify a credential name to associate the user name and password credentials to access a remote node, to perform super user operations as a <code>sudo</code> user by specifying a <code>sudo</code> user name and the path to the <code>sudo</code> binary, or to use an authentication plugin to access the remote node.
<code>-targetnode</code> <code>node_name</code> <code>-root</code> <code>-cred cred_name</code> <code>-sudouser</code> <code>sudo_user_name</code> <code>-sudopath</code> <code>sudo_binary_location</code> <code>-auth plugin_name</code> <code>plugin_args</code>	(Optional) You can specify the name of a target node in a remote cluster with no Fleet Patching and Provisioning Client on which to provision a working copy, where you want to run the upgraded database. If you choose to use the <code>-targetnode</code> parameter, then you must choose either <code>root</code> , a credential name, <code>sudo</code> , or an authentication plugin to access the remote node. Choose <code>-root</code> to perform super user operations as <code>root</code> . Alternatively, you can choose either to specify a credential name to associate the user name and password credentials to access a remote node, to perform super user operations as a <code>sudo</code> user by specifying a <code>sudo</code> user name and the path to the <code>sudo</code> binary, or to use an authentication plugin to access the remote node.
<code>eval</code>	(Optional) You can specify <code>eval</code> to evaluate the Zero Downtime Upgrade operation to see if it can succeed, but does not perform the operation.
<code>-ignoreprereq</code>	(Optional) You can use this parameter to instruct the <code>zdtupgrade</code> database command to ignore system prerequisites during the upgrade.
<code>-useractiondata</code> <code>user_action_data</code>	(Optional) You can use this parameter to specify a value to be passed to the <code>useractiondata</code> parameter of a user action script

Table A-21 (Cont.) rhpctl zdtupgrade database Command Parameters

Parameter	Description
-dbuaargs	<p>(Optional) If you do not specify the AutoUpgrade Utility for the upgrade with the <code>-autoupg</code> parameter, so that Database Upgrade Assistant (DBUA) is used for the upgrade, then you can specify arguments to pass to DBUA. If you specify <code>-autoupg</code>, then this argument is not available.</p> <p>For example, if the user account with which you are running Zero Downtime Upgrade If your account does not have SYSDBA privileges, or you do not have operating system authentication set up, then you can use the following syntax to connect, where <i>mydb</i> is your Oracle Database SID, <i>username</i> is a user name with SYSDBA privileges, and <i>password</i> is that user name's password:</p> <pre>-sysDBAUserName - username -sysDBAPassword - password</pre>
[-autoupg [-upgtimezone [yes no] [-runutlrp [yes no]]	<p>(Optional) Specifies that you want to use the AutoUpgrade utility for the upgrade. If you select this option, then provide the following arguments:</p> <p><code>upgtimezone [yes no]</code> Specify <i>yes</i> to upgrade the timezone during the upgrade, or <i>no</i> to skip the timezone upgrade.</p> <p>If the Pre-Upgrade Information Tool instructs you to upgrade the time zone files after completing the database upgrade, then you can select this argument to enable the Zero Downtime Upgrade to upgrade the time zone file after the upgrade completes.</p> <p><code>runutlrp [yes no]</code> Specify <i>yes</i> to run the <code>utlrp.sql</code> script after the upgrade to revalidate the packages again., or select <i>no</i> to skip the timezone upgrade.</p> <p>Oracle recommends that you run the <code>utlrp.sql</code> script after you install, patch, or upgrade a database, to identify and recompile invalid objects.</p>

rhpctl update exadata

Patches an Oracle Exadata system.

Syntax

```
rhpctl update exadata [-image exadata_image_name]
                        [dbnodes [-patchmgrloc patch_mgr_loc] [-cells cell_list]
                        [-ibswitches ibswitch_list]]
                        [-iso_repo iso_image_name] [-client client_name]
                        [-batches list_of_batches | -continue | -abort] [-eval]
```

Parameters

Table A-22 rhpctl update exadata Command Parameters

Parameter	Description
-image <i>exadata_image_name</i>	Specify the name of an Oracle Exadata image. This image should have already been deployed to all the database nodes of the target machine.
-dbnodes	Specifies the database servers to patch.
-patchmgrloc <i>patch_mgr_loc</i>	Specifies the patch manager location.
-cells	Specifies the storage servers to patch.
-ibswitches	Specifies the IB switches to patch.
-iso_repo <i>iso_image_name</i>	Specifies the ISO image name.
-client <i>client_name</i>	Specify the name of the cluster in which you want to update database nodes.
-batches <i>list_of_batches</i>	Optionally, you can specify a comma-delimited list of batches of nodes where each batch is a comma-delimited list of node names enclosed in parentheses and node names are enclosed in double quotation marks (") in the format: "(nA,nB,...),(...,nY,nZ)".
-continue	Update Oracle Exadata on the next batch of nodes.
-abort	Abort the ongoing update operation.
-eval	Evaluate the command without actually running the command.

Usage Notes

Use the `rhpctl update exadata` command to perform only database node patching.

 **See Also:**

[Combined Oracle Exadata Database Node and Grid Infrastructure Patching](#) for information about Oracle Exadata database node patching

Example

The following example performs database node patching on a client cluster.

```
$ rhpctl update exadata image -image EXADATAIMAGEV1
   -iso_repo p28802055_192000_Linux-x86-64.zip
   -patchmgrloc /patchMgr/dbserver_patch_19.190306 -client CLIENT1 -
   batches "(rac07box1)"
```

rhpctl addnode gihome

Adds one or more nodes to an Oracle Grid Infrastructure installation.

Syntax

```

rhpctl addnode gihome {-workingcopy workingcopy_name | -client
cluster_name}
  -newnodes node_name:node_vip[:node_role]
[ ,node_name:node_vip[:node_role]...]
  {-root | -cred cred_name | -sudouser sudo_user_name
  -sudopath sudo_binary_location |
  -auth plugin_name [-arg1 name1:value1 [-arg2 name2:value2 ...]]}
  [-targetnode node_name] [-force] [-setupssh] [-useractiondata
user_action_data]
  [-eval] [-schedule {timer_value | NOW}]

```

Parameters

Table A-23 rhpctl addnode gihome Command Parameters

Parameter	Description
-workingcopy <i>workingcopy_name</i>	Specify the name of the working copy of the active Oracle Grid Infrastructure home that you want to install and configure on the specified node.
-client <i>cluster_name</i>	Alternatively, you can specify the name of the client cluster to which to add cluster nodes.
-node <i>node_list</i>	Specify a comma-delimited list of nodes on which Oracle Clusterware will be provisioned in the following format: <i>node_name:node_vip[:node_role]</i> [, <i>node_name:node_vip[:node_role]</i> ...]
-root - cred <i>cred_name</i> -sudouser <i>sudo_user_name</i> -sudopath <i>sudo_binary_location</i> -auth <i>plugin_name</i> <i>plugin_args</i>	You must choose either <i>root</i> , a credential name, <i>sudo</i> , or an authentication plugin to access the remote node. Choose <i>-root</i> to perform super user operations as <i>root</i> . Alternatively, you can choose either to specify a credential name to associate the user name and password credentials to access a remote node, to perform super user operations as a <i>sudo</i> user by specifying a <i>sudo</i> user name and the path to the <i>sudo</i> binary, or to use an authentication plugin to access the remote node.
-targetnode <i>node_name</i>	Optionally, you can specify the name of a node in a remote cluster that has no Fleet Patching and Provisioning Client.
-force	Optionally, you can use this parameter to forcibly add nodes ignoring any previously failed add-node operation.
-setupssh	Sets up passwordless SSH user equivalence on the remote nodes for the provisioning user.
-useractiondata <i>user_action_data</i>	Optionally, you can pass a value to the <i>useractiondata</i> parameter of the user action script.
-eval	Optionally, you can use this parameter to evaluate the impact of this command on the system without actually running the command.
-schedule { <i>timer_value</i> NOW}	Optionally, you can schedule a time to run this command in ISO-8601 format. For example: 2018-01-21T19:13:17+05. If NOW is specified, then the job is scheduled immediately.

Usage Notes

- You can specify the target for the operation using the working copy name or, if the target is a Fleet Patching and Provisioning Client, then using the client cluster name.
- You must provide either `root` credentials, a credential name, a `sudo` user, or an authentication plugin.
- A target node is required if the target cluster is an Oracle Clusterware 11g release 2 (11.2) or 12c release 1 (12.1) cluster and must be the node name of an existing cluster node.

rhpcctl deletenode gihome

Removes one or more nodes from an Oracle Grid Infrastructure installation.

Syntax

```
rhpcctl deletenode gihome {-workingcopy workingcopy_name | -client
cluster_name}
  -node node_list {-root | -sudouser sudo_username -sudopath
sudo_binary_path
  -cred cred_name | -auth plugin_name [-arg1 name1:value1...]}
  [-targetnode node_name] [-useractiondata user_action_data]
  [-eval] [-schedule {timer_value | NOW}]
```

Parameters

Table A-24 rhpcctl deletenode gihome Command Parameters

Parameter	Description
<code>-workingcopy workingcopy_name</code>	Specify the name of a working copy of the Oracle Grid Infrastructure home that you want to remove from the specified node.
<code>-client cluster_name</code>	Alternatively, you can specify the name of the client cluster from which to remove cluster nodes.
<code>-node node_list</code>	Specify a comma-delimited list of node names from which to delete Oracle Grid Infrastructure.
<code>-root -sudouser sudo_username -sudopath sudo_binary_path -cred cred_name -auth plugin_name [-arg1 name1:value1...]</code>	You must choose either <code>sudo</code> or <code>root</code> to access the remote nodes. If you choose <code>sudo</code> , then you must specify a user name to run super-user operations, and a path to the location of the <code>sudo</code> binary. Optionally, you can choose to specify a credential name to associate the user and password credentials to access a remote node. Alternative to <code>-sudouser</code> , <code>-root</code> , or <code>-cred</code> , you can use <code>-auth</code> to specify an authentication plugin to access a remote node.
<code>-targetnode node_name</code>	Name of a node in a remote cluster with no Fleet Patching and Provisioning Client.
<code>-useractiondata user_action_data</code>	Optionally, you can pass a value to the <code>useractiondata</code> parameter of the user action script.

Table A-24 (Cont.) rhpctl deletenode gihome Command Parameters

Parameter	Description
-eval	Optionally, you can use this parameter to evaluate the impact of this command on the system without actually running the command.
-schedule { <i>timer_value</i> NOW}	Optionally, you can schedule a time to run this command in ISO-8601 format. For example: 2018-01-21T19:13:17+05. If NOW is specified, then the job is scheduled immediately.

Usage Notes

- You can specify the target for the operation using the working copy name or, if the target is a Fleet Patching and Provisioning Client, then using the client cluster name.
- You must provide either `root` credentials or a `sudo` user.
- A target node is required if the target cluster is an Oracle Clusterware 11g release 2 (11.2) or 12c release 1 (12.1) cluster and must be the node name of an existing cluster node.

rhpctl move gihome

Moves the Oracle Grid Infrastructure software stack from one home to another.

Syntax

```
rhpctl move gihome {-destwc destination_workingcopy_name |
  -desthome destination_oracle_home_path}
  {{-sourcewc source_workingcopy_name | -sourcehome oracle_home_path}
  [-targetnode target_node_name] [-ignorewcpatches] [-nonrolling] [-
keepplacement]
  [-auto -dbhomes mapping_of_Oracle_homes] [-dblist db_name_list
  | -excludedblist db_name_list] [-nodatapatch] [-disconnect]
  [-stopoption stop_option] [-drain_timeout timeout]
  [-dbsinparallel number_of_instances] [-raconetimeout timeout]]
  [-batches list_of_batches | -smartmove [-saf availability]
[separate]]
  [-eval] [-schedule {timer_value | NOW}]
  [[-aupath gold_image_path [-agpath read_write_path]] | [-tgip [-
nodriverupdate]]]
  [-ignoremissingpatches patch_name1[,patch_name2...]] | -continue |
-revert | -abort | -forcecomplete}
  [-root | -cred cred_name | -sudouser sudo_username -sudopath
path_to_sudo_binary
  | -auth plugin_name [-arg1 name1:value1 [-arg2 name2:value2
...]]]
  [-cleanpids] [-useractiondata user_action_data]
  [-image image_name] [-smtpfrom "address"] [-smtpto "adresse1
adresse2 ..."]
  [-iso_repo iso_image] [-patchmgrloc patch_mgr_loc] [-
ignoredbstartererror]
```


Parameters

Table A-25 rhpctl move gihome Command Parameters


Parameter	Description
<code>-destwc</code> <i>destination_workingc</i> <i>opy_name</i>	Specify the name of the destination working copy to which you want to move Oracle Grid Infrastructure.
<code>-desthome</code> <i>destination_oracle_h</i> <i>ome_path</i>	Alternative to specifying the name of the destination working copy, you can specify the path to the destination for the move of an Oracle home when you are moving the Oracle Grid Infrastructure home.
 Note: This option is valid only for local mode execution of FPP automaton and not available with regular FPP.	
<code>-sourcewc</code> <i>working_copy_name</i>	If you want to move Oracle Grid Infrastructure from a working copy, then specify the name of the source working copy from which you want to move the Grid home.
<code>-sourcehome</code> <i>oracle_home_path</i>	If you are moving Oracle Grid Infrastructure from an unmanaged (not provisioned by Fleet Patching and Provisioning) Oracle home, then specify the path to the Oracle home from which you want to move Oracle Grid Infrastructure.
<code>-targetnode</code> <i>target_node_name</i>	Name of a node in a remote cluster with no Fleet Patching and Provisioning Client.
<code>-ignorewcpatches</code>	Use this parameter to ignore if the patched working copy is missing some patches which are present in the source path or working copy.
<code>-nonrolling</code>	Use this parameter to move the Oracle home in a non-rolling fashion.
<code>-keepplacement</code>	Specify this parameter to ensure that services of administrator-managed Oracle RAC or Oracle RAC One Node databases are running on the same instances before and after the move operation.
<code>-auto -dbhomes</code> <i>mapping_of_oracle_ho</i> <i>mes</i>	Specify this parameter to automatically patch databases when you patch Oracle Grid Infrastructure.
<code>-dblist</code> <i>db_name_list</i>	Specify the unique names of the databases (DB_UNIQUE_NAME without DB_DOMAIN) that you want to move to the patched working copy. Note: If you are moving a non-clustered (single-instance) database, then, for the value of the <code>-dbname</code> parameter, you must specify the <i>SID</i> of the database instead of the database name.
<code>-excludedblist</code> <i>db_name_list</i>	Alternative to using the <code>-dbname</code> parameter, you can use the <code>-excludedblist</code> parameter to patch all databases except specific databases.

Table A-25 (Cont.) rhpctl move gihome Command Parameters

Parameter	Description
-nodatapatch	Optionally, you can use this parameter to indicate not to run datapatch for databases being moved.
-disconnect	Optionally, you can use this parameter to disconnect all sessions before stopping or relocating services.
-stopoption <i>stop_option</i>	Optionally, you can choose one of the following stop options for the database: ABORT, IMMEDIATE, NORMAL, TRANSACTIONAL, or TRANSACTIONAL_LOCAL.
-drain_timeout <i>session_drain_time</i>	Optionally, you can use this parameter to specify a service drain timeout, in seconds.
-batches <i>list_of_batches</i>	Optionally, you can specify a comma-delimited list of batches of nodes (where each batch is a comma-delimited list of node names enclosed in parentheses) enclosed in double quotation marks (" ") in the format: " (nA,nB,...) , (... ,nY,nZ) ".
-smartmove [-saf <i>availability</i>]	Alternatively, you can use the -smartmove parameter to auto-generate a list of batches of nodes and move databases by restarting instances after each batch. Optionally, you can use the -saf parameter to specify the service availability factor, which is the minimum percentage of instances on which a service must remain running during the move.
-continue	Use this parameter to continue restarting the Oracle Clusterware stack on the next batch of nodes.
-revert	Use this parameter to revert back to before the move operation.
-abort	Use this parameter to abort an ongoing move operation.
-forcecomplete	Use this parameter to mark the move operation as complete after completing it manually.
-root - <i>cred cred_name</i> -sudouser <i>sudo_user_name</i> -sudopath <i>sudo_binary_location</i>	If you choose to use the -targetnode parameter, then you must choose either root, a credential name, sudo, or an authentication plugin to access the remote node. Choose -root to perform super user operations as root. Alternatively, you can choose either to specify a credential name to associate the user name and password credentials to access a remote node, to perform super user operations as a sudo user by specifying a sudo user name and the path to the sudo binary, or you can use -auth to use an authentication plugin to access the remote node.
-auth <i>plugin-</i> <i>name</i> [-arg1 <i>name1:value1</i> [-arg2 <i>name2:value2 ...</i>]]	Use an authentication plugin to access the remote node. Optionally provide a list of arguments to the plugin.
-cleanpids	When using a persistent home path for both the source and destination working copies, specify -cleanpids to ensure processes are stopped completely on the source home.
-useractiondata <i>user_action_data</i>	Optionally, you can pass a value to the useractiondata parameter of the user action script.

Table A-25 (Cont.) rhpctl move gihome Command Parameters

Parameter	Description
-schedule { <i>timer_value</i> NOW}	Optionally, you can use this parameter to schedule a time to run this operation, in ISO-8601 format, as in the following example: 2018-07-25T19:13:17+05 If NOW is specified, then the job is scheduled immediately.
-eval	Use this parameter to evaluate the rhpctl move gihome command and print automatically generated batches of nodes and the sequence of moves without actually running the command.
-dbsinparallel <i>number_of_instances</i>	Specifies the number of database instances that can be started in parallel on a given node.
-raconettimeout <i>timeout</i>	the Oracle RAC One Node database relocation timeout in minutes.
-tgip [- nodriverupdate]	Performs a transparent move of the Oracle Grid Infrastructure home. The optional -nodriverupdate option skips the patching of the drivers if the patch contains a driver patch.
- ignoremissingpatches <i>patch_name1</i> [, <i>patch_name2</i> ...]	Proceed with the move and/or upgrade although the specified patches, which are present in the source path or working copy, may be missing from the destination path or working copy.
-image <i>image_name</i>	Specifies the name of the image. For Oracle Exadata, this is the Exadata image name.
-smtpfrom " <i>address</i> "	Optionally, you can specify an email address enclosed in double quotation marks (") from which Oracle Fleet Patching and Provisioning sends patch manager notifications.
-smtpto " <i>adresse1</i> <i>adresse2</i> ..."	Optionally, you can specify several email address enclosed in double quotation marks (") to which Oracle Fleet Patching and Provisioning sends patch manager notifications.
-iso_repo <i>iso_image</i>	Specifies the image in the ISO repository.
-patchmgrloc <i>patch_mgr_loc</i>	Specifies the patch manager location.
-ignoredbstarterror	Use this parameter to ignore the database startup errors during Oracle Grid Infrastructure patching.

Usage Notes

If you choose to use the -schedule parameter, then you must run this command on the Fleet Patching and Provisioning Server.

Example

Assume there is a target cluster running Oracle Grid Infrastructure 12c release 1 (12.1.0.2) from a working copy named `grid12102wcopy`, and one of the nodes in the cluster is named `bposvr141`. After provisioning the patched working copy, called

grid12102PSU (using the `-softwareonly` parameter with the `rhpcctl add workingcopy` command), move the Grid home to the patched working copy, as follows:

```
$ rhpcctl move gihome -sourcewc grid12102wcpy -destwc grid12102PSU -root
-targetnode bposvr141
```

rhpcctl upgrade gihome

Upgrades the Oracle Grid Infrastructure from a source working copy or source home path to a destination working copy.

Syntax

```
rhpcctl upgrade gihome {-sourcewc source_workingcopy_name |
    -sourcehome oracle_home_path -targetnode target_node_name}
    -destwc destination_workingcopy_name
    [-revert {-root | -sudouser sudo_user_name -sudopath
sudo_binary_location}
    -cred cred_name |
    -auth plugin_name [-arg1 name1:value1...] [-arg2 name2:value2
...]]}
    [-ignoreprereq] [-useractiondata user_action_data]
    [-eval] [-batches list_of_batches] [-abort | -continue]
    [-schedule {timer_value | NOW}]
    [-ignoremissingpatches patch_name1[,patch_name2...]]
    [-gimrwc gimr_wc_name]
    [-ignorecvcheck]
```

Parameters

Table A-26 rhpcctl upgrade gihome Command Parameters

Parameter	Description
<code>-sourcewc</code> <i>source_workingcopy_name</i>	Specify the name of the source working copy from which the Oracle Grid Infrastructure home needs to be upgraded.
<code>-sourcehome</code> <i>oracle_home_path</i>	Alternative to specifying the name of the source working copy, you can specify the path to the unmanaged Oracle Grid Infrastructure home.
<code>-targetnode</code> <i>target_node_name</i>	In addition to specifying the source Oracle Grid Infrastructure home, you must also specify a node that is in a remote cluster that has no Oracle Fleet Patching and Provisioning Client.
<code>-destwc</code> <i>destination_workingcopy_name</i>	Specify the name of the destination working copy to which the Oracle Grid Infrastructure home is to be upgraded.
<code>-revert</code>	Specify this option to downgrade after a failed upgrade of Oracle Grid Infrastructure.

Table A-26 (Cont.) rhpctl upgrade gihome Command Parameters

Parameter	Description
<code>-root</code> <code>-sudouser</code> <code>sudo_username</code>	If you choose to use the <code>-targetnode</code> parameter, then you must choose either <code>sudo</code> or <code>root</code> to access the remote node.
<code>-sudopath</code> <code>sudo_binary_path</code> <code>-cred cred_name</code>	If you choose <code>sudo</code> , then you must specify a user name to run super-user operations, and a path to the location of the <code>sudo</code> binary. Optionally, you can choose to specify a credential name to associate the user and password credentials to access a remote node. Alternative to <code>-sudouser</code> , <code>-root</code> , or <code>-cred</code> , you can use <code>-auth</code> to specify an authentication plugin to access a remote node.
<code>-auth plugin-name</code> [<code>-arg1 name1:value1</code> [<code>-arg2 name2:value2</code> ...]]	Use an authentication plugin to access the remote node. Optionally provide a list of arguments to the plugin.
<code>-ignoreprereq</code>	Use this parameter to ignore the CVU prerequisite checks.
<code>-schedule</code> { <code>timer_value</code> <code>NOW</code> }	Optionally, you can schedule a time to run this command in ISO-8601 format. For example: 2018-01-21T19:13:17+05. If <code>NOW</code> is specified, then the job is scheduled immediately.
<code>-useractiondata</code> <code>user_action_data</code>	Value to be passed to <code>useractiondata</code> parameter of the <code>useraction</code> script.
<code>-eval</code>	Evaluate without executing the command.
<code>-batches</code> <code>list_of_batches</code>	List of batches of nodes in the format: "(Ba), ..., (Bz)".
<code>-abort</code> <code>-continue</code>	Abort the ongoing move operation or continue restarting the CRS stack on the next batch of nodes.
<code>-ignoremissingpatches</code> <code>patch_name1</code> [, <code>patch_name2</code> ...]	Proceed with the move and/or upgrade although the specified patches, which are present in the source path or working copy, may be missing from the destination path or working copy.
<code>-gimrwc</code> <code>gimr_wc_name</code>	Name of the destination working copy to which the Grid Infrastructure Management Repository database needs to be upgraded.
<code>-ignorecvucheck</code>	Ignore errors during post Oracle Grid Infrastructure upgrade CVU check.

 **Note:**

For self upgrade of FPPS to 21c, you must use the `rhpctl.sh` script from the Oracle Grid Infrastructure 21c home. You should also specify the `-gimrwc` parameter.

rhpcctl add image

Use the `rhpcctl add image` command to create an image from an existing working copy and add it to the list of existing images on the Fleet Patching and Provisioning Server configuration.

Syntax

```
rhpcctl add image -image image_name -workingcopy working_copy_name
  [-imagetype image_type] [-series series_name] [-state {TESTABLE |
  RESTRICTED | PUBLISHED}]
```

Parameters

Table A-27 rhpcctl add image Command Parameters

Command Option	Description
<code>-image <i>image_name</i></code>	Specify the name of the image that you want to add.
<code>-workingcopy <i>working_copy_name</i></code>	Specify the name of the working copy from which to create the image.
<code>-imagetype <i>image_type</i></code>	Specify the software type. ORACLEDBSOFTWARE (default) for Oracle Database software, ORACLEGISoftware for Oracle Grid Infrastructure software, ORACLEGGSoftware for Oracle GoldenGate software, LINUXOS for Linux operating system ISO, or SOFTWARE for all other software. If you use custom image types, then specify the name of your image type.
<code>-series <i>series_name</i></code>	If you want to add an image to an image series, then specify the name of an image series.
<code>-state {TESTABLE RESTRICTED PUBLISHED}</code>	Specify the state of the image.

Usage Notes



See Also:

[Patching Oracle Database Software](#) for details about how to use this command in the workflow for creating patched Oracle Database software homes

Example

An example of this command is:

```
$ rhpcctl add image -image DB12201_PATCH -workingcopy
temp_wcpy_db12201_patch
```

rhpcctl allow image

Allows access to an image by a user or a role.

Syntax

```
rhpcctl allow image -image image_name {-user user_name [-client  
cluster_name]  
| -role role_name}
```

Parameters

Table A-28 rhpcctl allow image Command Parameters

Parameter	Description
-image <i>image_name</i>	Specify the name of the image to which you want to allow access.
-user <i>user_name</i> [-client <i>cluster_name</i> -role <i>role_name</i>]	Specify the either of the following: <ul style="list-style-type: none"> A user for which you want to allow access to the image and, optionally, the cluster name of the client cluster with the user. The role for which you want to allow access to the image.

Examples

To allow access to an image named PRODIMAGE:

```
$ rhpcctl allow image -image PRODIMAGE -user mjk -client GHCL
```

rhpcctl delete image

Deletes a specific image.

Syntax

```
rhpcctl delete image -image image_name [-schedule {timer_value | NOW}]
```

Usage Notes

- Specify the name of the image you want to delete
- Optionally, you can use the `-schedule` parameter to schedule a time to run this operation, in ISO-8601 format, as in the following example:

```
2018-07-25T19:13:17+05
```

If you choose to use this parameter, then you must run this command on the Fleet Patching and Provisioning Server. If `NOW` is specified, then the job is scheduled immediately.

- This command will fail if the image belongs to one or more series

- This command will fail if there are any provisioned working copies based on this image

Example

The following example deletes an image named PRODIMAGEV0:

```
$ rhpctl delete image -image PRODIMAGEV0
```

rhpctl deploy image

Deploys an image to a specific node in a client cluster.

Syntax

```
rhpctl deploy image -image image_name [-targetnode node_name
  {-sudouser sudo_user_name -sudopath sudo_binary_path | -root}]
```

Parameters

Table A-29 rhpctl deploy image Command Parameters

Parameter	Description
-image <i>image_name</i>	Specify the name of the image you want to deploy.
-targetnode <i>node_name</i>	Optionally, you can specify the name of a node to which you want to deploy the image. This parameter is required if the node hosting the home is not a Fleet Patching and Provisioning Client.
-sudouser <i>sudo_user_name</i> -sudopath <i>sudo_binary_path</i> - root]	If you use the -targetnode parameter, then you must specify either sudo or root to perform super user operations.

Usage Notes

You can only run this command from a Fleet Patching and Provisioning Server.

Example

The following example deploys an Oracle Database Appliance image to a node:

```
$ rhpctl deploy image -image ODA1 -targetnode racgbox1 -root
```

rhpctl disallow image

Disallows access to an image by a user or a role.

Syntax

```
rhpctl disallow image -image image_name {-user user_name [-client
client_name]
| -role role_name}
```

Parameters

Table A-30 rhpctl disallow image Command Parameters

Parameter	Description
-image <i>image_name</i>	Specify the name of the image to which you want to disallow access.
-user <i>user_name</i> [-client <i>client_name</i> -role <i>role_name</i>]	Specify either of the following: <ul style="list-style-type: none"> A user for which you want to disallow access to the image and, optionally, the cluster name of the client cluster with the user. The role for which you want to disallow access to the image.

Examples

To disallow access to an image:

```
$ rhpctl disallow image -image PRODIMAGE -user mjk -client GHC1
```

rhpctl import image

Creates an image on the Fleet Patching and Provisioning Server.

Use the `rhpctl import image` command to create an image by copying the entire software contents from the specified path to the Oracle Fleet Patching and Provisioning Server.

Syntax

```
rhpctl import image -image image_name
  {-path path | -zip zipped_home_path | -notify [-cc user_list]}
  [-imagetype image_type] [-pathowner user_name] [-version
software_version]
  [-state {TESTABLE | RESTRICTED | PUBLISHED}] [-location
zipped_home_path]
  [-client cluster_name]
  [-targetnode node_name [-sudouser sudo_user_name -sudopath
sudo_binary_path |
  -root | cred cred_name |
  -auth plugin_name [-arg1 name1:value1 [-arg2 name2:value2 ... ]]]]
  [-useractiondata user_action_data] []
  [-series series_name]
```

Parameters

Table A-31 rhpctl import image Command Parameters

Parameter	Description
-image <i>image_name</i>	Specify the name of the image that you want to add.
-path <i>path</i>	Specify the absolute path location of the software home that you want to import. For Oracle Database images, this is the ORACLE_HOME.
-zip <i>zipped_home_path</i>	Specify the absolute path of the compressed software home to be imported (a ZIP or TAR file).
-notify [-cc <i>users_list</i>]	Send an email notification. Specify a list of users to whom email notifications is sent (in addition to the owner of working copy).
-imagetype <i>image_type</i>	Specify the software type. Use ORACLEDBSOFTWARE (default) for Oracle database software, ORACLEGISoftware for Oracle Grid Infrastructure software, ODAPATCHSOFTWARE for engineered systems (Oracle Data Appliance), EXAPATCHSOFTWARE for Oracle Exadata software, or SOFTWARE for all other software. For a custom image type, use the image type name.
-version <i>software_version</i>	Optionally, you can specify the version of the software you are importing.
-pathowner <i>user_name</i>	Specify the user with read access to the files and directories under the specified path. Note: This parameter is applicable only for non-Oracle database software homes.
-state {TESTABLE RESTRICTED PUBLISHED}	Specify whether the state of the image is testable, restricted, or published.
-location <i>zipped_home_path</i>	Location of the compressed image file on the target.
-client <i>cluster_name</i>	Specify the name of the client cluster.
-targetnode <i>node_name</i>	Specify the name of the node from which you want to import the image. This parameter is required if the node hosting the home is not an Fleet Patching and Provisioning Client.
-sudouser <i>sudo_user_name</i> -sudopath <i>sudo_binary_path</i> - root]	If you use the -targetnode parameter, then you must specify either sudo or root to perform super user operations.
-auth <i>plugin-</i> <i>name</i> [-arg1 <i>name1:value1</i> [-arg2 <i>name2:value2</i> ...]]	Use an authentication plugin to access the remote node. Optionally provide a list of arguments to the plugin.
-useractiondata <i>user_action_data</i>	Optionally, you can pass a value to the useractiondata parameter of the user action script.
-series <i>series_name</i>	The name of the series.

Usage Notes

- You can only run this command on a Fleet Patching and Provisioning Server.
- When you import an Oracle Database or Oracle Grid Infrastructure software home, the version of the home must be one of the versions that Fleet Patching and Provisioning supports for provisioning and patching.

Examples

The following example imports an image:

```
$ rhpctl import image -image PRODIMAGEV1 -path /u01/app/product/12.1.0/dbhome -pathowner orcl
```

The following example imports an engineered system image:

```
$ rhpctl import image -image ODA1 -imagetype ODAPATCHSOFTWARE -path /tmp/ODAPatchBundle -version 12.1.2.8.0
```

rhpctl instantiate image

Requests copies of gold images from a peer Fleet Patching and Provisioning Server.

Syntax

```
rhpctl instantiate image -server server_cluster_name {-image image_name | -series series_name | -imagetype image_type | -all}
```

Parameters

Table A-32 rhpctl instantiate image Command Parameters

Parameter	Description
-server <i>server_cluster_name</i>	Specify a Fleet Patching and Provisioning Server cluster from which you want to request images.
-image <i>image_name</i> -series <i>series_name</i> -imagetype <i>image_type</i> -all	You can request copies of gold images from a peer Fleet Patching and Provisioning Server, specifically, by image name, series name, or image type. Alternatively, you can use the -all parameter to request copies of all gold images from the peer Fleet Patching and Provisioning server. If you choose to request images by image type, then specify ORACLEDBSOFTWARE (default) for Oracle Database software, ORACLEGISoftware for Oracle Grid Infrastructure software, ORACLEGGSoftware for Oracle GoldenGate software, and SOFTWARE for all other software. For a custom image type, use the image type name.

Usage Notes

- User actions associated with an image being copied are not themselves copied.
- Groups configuration of a gold image is replicated in copies sent to peers.

- Copies of gold images are in the PUBLISHED state.

rhpcctl modify image

Modifies the configuration details of an image.

Syntax

```
rhpcctl modify image -image image_name -imagetype image_type
```

Parameters

Table A-33 rhpcctl modify image Command Parameters

Parameter	Description
<code>-image <i>image_name</i></code>	Specify the name of the image that you want to modify.
<code>-imagetype <i>image_type</i></code>	You can modify the software type. Use ORACLEDBSOFTWARE (default) for Oracle database software, ORACLEGISoftware for Oracle Grid Infrastructure software, or SOFTWARE for all other software. For a custom image type, use the image type name.

rhpcctl query image

Displays the configuration of an existing image.

Syntax

```
rhpcctl query image {[[-image image_name [-dbtemplate]] | [[-imagetype image_type [-version version] [-platform platform]] | [[-server server_cluster_name | -client client_name | -local] | -drift} [[-rhpsrver rhps_regex ]]
```

Parameters

Table A-34 rhpcctl query image Command Parameters

Parameter	Description
<code>-image <i>image_name</i> [-dbtemplate]</code>	Specify the name of the image you want to query. Optionally, you can use the <code>-dbtemplate</code> parameter to display template file names in the default template directory.
<code>-imagetype <i>image_type</i></code>	Specify the software type. Use ORACLEDBSOFTWARE (default) for Oracle database software, ORACLEGISoftware for Oracle Grid Infrastructure software, or SOFTWARE for all other software. For a custom image type, use the image type name.
<code>-version <i>version</i></code>	Specify the version of the image software you are querying.
<code>-platform <i>platform</i></code>	Specify the operating system platform to which the image corresponds.
<code>-server <i>server_cluster_name</i></code>	Specify the name of the server cluster to which the image corresponds.

Table A-34 (Cont.) rhpctl query image Command Parameters

Parameter	Description
<code>-client <i>client_name</i></code>	If this parameter is used with the <code>-image</code> option, the command checks if the specified client has the given image instantiated on it. Otherwise, the use of the parameter lists the images instantiated on the given client.
<code>-local</code>	List the images stored on the current client.
<code>-drift</code>	List the the bug fixes not included in the golden image.
<code>-rhpserver <i>rhps_regex</i></code>	Specify a regular expression to match the cluster name of the servers where the operation must be executed.

Usage Notes

If you use the `-version` parameter, then the version must have five fields, such as 12.1.0.2.4.

If you use the `-platform` parameter, then you can use `Linux_AMD64`, `Linux_S390`, `Linux_PPC`, `IBM_AIX_PPC64`, `HP_IA64`, `Linux_Itanium`, `Solaris_SPARC64`, `Linux_LOP`, and `Intel_Solaris_AMD64`

The `-rhpserver` parameter indicates where the operation should be executed and the `-server` parameter indicates what the operation should be about. When `-rhpserver` is used, the command is executed on the servers whose name matches the regular expression provided. When `-server` is used, the command is about the server provided. For example:

- The following command executes locally and lists the images that have been replicated to `peerA`

```
rhpctl query image -server peerA
```

- The following command executes on `peerA` and lists the images have been configured on `peerA`

```
rhpctl query image -rhpserver peerA
```

- The following command executes on all servers and lists the images that each server has replicated on `peerA`

```
rhpctl query image -server peerA -rhpserver .'
```

When issuing a command for a peer server using the `-rhpserver` option, the user running the command must be an existing user of the peer server and the user must have a required role. To enable a user from a peer server to run commands on the local server, run the `rhpctl grant role` command to grant a required role to the peer server user and to specify the cluster name of the peer server to which the user belongs. For example:

```
$ rhpctl grant role -role role_name -user user_name -client cluster_name
```

To add multiple users, run the following command:

```
$ rhpctl grant role -client cluster_name -maproles
role=user_name[+user_name...][,role=user_name[+user_name...]]...
```

For information about granting roles with RHPCTL, refer to [rhpctl grant role](#)

rhpctl promote image

Promotes an image.

Syntax

```
rhpctl promote image -image image_name -state {TESTABLE | RESTRICTED |
PUBLISHED}
```

Parameters

Table A-35 rhpctl promote image Command Parameters

Parameter	Description
-image <i>image_name</i>	Specify the name of the image that you want to promote.
-state {TESTABLE RESTRICTED PUBLISHED}	Specify one of the following as the name of the state of the image: TESTABLE: RESTRICTED: PUBLISHED:

Example

To promote an image named PRODIMAGE:

```
$ rhpctl promote image -image PRODIMAGE -state RESTRICTED
```

rhpctl unstantiate image

Stops updates for previously requested images from a peer Fleet Patching and Provisioning Server.

Syntax

```
rhpctl unstantiate image -server server_cluster_name {-image
image_name
| -series series_name | -imagetype image_type | -all}
```

Parameters

Table A-36 rhpctl unstantiate image Command Parameters

Parameter	Description
<code>-server</code> <code>server_cluster_name</code>	Specify a Fleet Patching and Provisioning Server cluster from which you want to stop updates.
<code>-image image_name</code> <code>-series series_name</code> <code>-imagetype</code> <code>image_type</code> <code>-all</code>	You can updates from a peer Fleet Patching and Provisioning Server, specifically, by image name, series name, or image type. Alternatively, you can use the <code>-all</code> parameter to stop updates from the peer Fleet Patching and Provisioning server. If you choose to stop updates by image type, then specify <code>ORACLEDBSOFTWARE</code> (default) for Oracle Database software, <code>ORACLEGISoftware</code> for Oracle Grid Infrastructure software, <code>ORACLEGGSoftware</code> for Oracle GoldenGate software, and <code>SOFTWARE</code> for all other software. For a custom image type, use the image type name.

rhpctl add imagetype

Configures a new image type and its associated user actions.

Syntax

```
rhpctl add imagetype -imagetype image_type -basetype {SOFTWARE |
ORACLEGISoftware | ORACLEDBSOFTWARE | ORACLEGGSoftware}
[-useractions user_action_list]
```

Parameters

Table A-37 rhpctl add imagetype Command Parameters

Parameter	Description
<code>-imagetype</code> <code>image_type</code>	Specify the name of the image type you are creating.
<code>-basetype</code> {SOFTWARE ORACLEGISoftware ORACLEDBSOFTWARE ORACLEGGSoftware}	Specify a base image type on which the image type you are creating is based. Use <code>ORACLEDBSOFTWARE</code> (default) for Oracle Database software, <code>ORACLEGISoftware</code> for Oracle Grid Infrastructure software, <code>ORACLEGGSoftware</code> for Oracle GoldenGate software, and <code>SOFTWARE</code> for all other software.
<code>-useractions</code> <code>user_action_list</code>	Specify a comma-delimited list of names of user actions

Example

To add a new image type:

```
rhpctl add imagetype -imagetype DB122_PATCH_TYPE -basetype ORACLEDBSOFTWARE
```

rhpcctl allow imagetype

Grants access to an image type to a user or a role.

Syntax

```
rhpcctl allow imagetype -imagetype image_type {-user user_name [-client  
cluster_name] | -role role_name}
```

Parameters

Table A-38 rhpcctl allow imagetype Command Parameters

Parameter	Description
-imagetype <i>image_type</i>	Specify the name of the image type to which you are granting access. Use ORACLEDBSOFTWARE (default) for Oracle database software, ORACLEGISoftware for Oracle Grid Infrastructure software, or SOFTWARE for all other software. For a custom image type, use the image type name.
-user <i>user_name</i>	Specify an operating system user to whom you are granting access to the image type. Either this parameter or the -role parameter is required.
-client <i>cluster_name</i>	Optionally, you can specify the name of the client cluster to which the operating system user belongs, if you choose to use the -user parameter.
-role <i>role_name</i>	Alternative to the -user parameter, you can specify a particular role to which to grant access to the image.

rhpcctl delete imagetype

Deletes an existing image type.

Syntax

```
rhpcctl delete imagetype -imagetype image_type
```

Usage Notes

Specify an image type to delete. You cannot delete any of the built-in image types.

rhpcctl disallow imagetype

Revokes access to an image type from a user or a role.

Syntax

```
rhpcctl disallow imagetype -imagetype image_type {-user user_name [-  
client cluster_name] | -role role_name}
```


Parameters

Table A-39 rhpctl disallow imagetype Command Parameters

Parameter	Description
<code>-imagetype</code> <i>image_type</i>	Specify the name of the image type from which you are revoking access. Use ORACLEDBSOFTWARE (default) for Oracle database software, ORACLEGISoftware for Oracle Grid Infrastructure software, or SOFTWARE for all other software. For a custom image type, use the image type name.
<code>-user</code> <i>user_name</i>	Specify an operating system user from whom you are revoking access to the image type. Either this parameter or the <code>-role</code> parameter is required.
<code>-client</code> <i>cluster_name</i>	Optionally, you can specify the name of the client cluster to which the operating system user belongs, if you choose to use the <code>-user</code> parameter.
<code>-role</code> <i>role_name</i>	Alternative to the <code>-user</code> parameter, you can specify a particular role from which to revoke access to the image.

rhpctl modify imagetype

Modifies the configuration of an image type.

Syntax

```
rhpctl modify imagetype -imagetype image_type -useractions  
user_action_list
```

Parameters

Table A-40 rhpctl modify imagetype Command Parameters

Parameter	Description
<code>-imagetype</code> <i>image_type</i>	Specify the name of the image type you want to modify. Use ORACLEDBSOFTWARE (default) for Oracle database software, ORACLEGISoftware for Oracle Grid Infrastructure software, ORACLEGGSoftware for Oracle GoldenGate software, or SOFTWARE for all other software. For a custom image type, use the image type name.
<code>-useractions</code> <i>user_action_list</i>	Specify a comma-delimited list of names of user actions

rhpctl query imagetype

Displays the configuration of an image type.

Syntax

```
rhpctl query imagetype -imagetype image_type [-rhpserver rhps_regex]
```

Parameters

Table A-41 rhpctl query imagetype Command Parameters

Parameter	Description
<code>-imagetype</code> <i>image_type</i>	Specify the name of the image type you want to query. Use <code>ORACLEDBSOFTWARE</code> (default) for Oracle database software, <code>ORACLEGISoftware</code> for Oracle Grid Infrastructure software, <code>ORACLEGGSoftware</code> for Oracle GoldenGate software, or <code>SOFTWARE</code> for all other software. For a custom image type, use the image type name.
<code>-rhpserver</code> <i>rhps_regex</i>	Specify a regular expression to match the cluster name of the servers where the operation must be executed.

Usage Notes

Specify the name of the image type you want to query. Use `ORACLEDBSOFTWARE` (default) for Oracle database software, `ORACLEGISoftware` for Oracle Grid Infrastructure software, or `SOFTWARE` for all other software. For a custom image type, use the image type name.

The `-rhpserver` parameter indicates where the operation should be executed and the `-server` parameter indicates what the operation should be about. When `-rhpserver` is used, the command is executed on the servers whose name matches the regular expression provided. When `-server` is used, the command is about the server provided. For example:

- The following command executes locally and lists the image types that have been replicated to `peerA`

```
rhpctl query imagetype -server peerA
```

- The following command executes on `peerA` and lists the image types have been configured on `peerA`

```
rhpctl query imagetype -rhpserver peerA
```

- The following command executes on all servers and lists the image types that each server has replicated on `peerA`

```
rhpctl query imagetype -server peerA -rhpserver .+'
```

When issuing a command for a peer server using the `-rhpserver` option, the user running the command must be an existing user of the peer server and the user must have a required role. To enable a user from a peer server to run commands on the local server, run the `rhpctl grant role` command to grant a required role to the peer server user and to specify the cluster name of the peer server to which the user belongs. For example:

```
$ rhpctl grant role -role role_name -user user_name -client cluster_name
```

To add multiple users, run the following command:

```
$ rhpctl grant role -client cluster_name -maproles
role=user_name[+user_name...][,role=user_name[+user_name...]....]
```

For information about granting roles with RHPCTL, refer to [rhpctl grant role](#)

rhpctl delete job

Deletes a specific scheduled job from the repository.

Syntax

```
rhpctl delete job [-jobid job_id] [-force]
```

Parameters

Table A-42 rhpctl delete job Command Parameters

Parameter	Description
-jobid <i>job_id</i>	Optionally, you can specify the job ID value for the job you want to delete that you obtained while scheduling the job. If you choose not to use this parameter, then RHPCTL deletes all jobs.
-force	Use this parameter to forcibly delete a job.

Usage Notes

You must run this command on the Fleet Patching and Provisioning Server.

Example

To delete a job with a job ID of 1:

```
$ rhpctl delete job -jobid 1
```

rhpctl query job

Queries the current status of a scheduled job with a specific job ID.

Syntax

```
rhpctl query job [-jobid job_id] [-status {EXECUTED | TIMER_RUNNING
| EXECUTING | UNKNOWN | TERMINATED}] [-client client_name] [-user
user_name]
[-since timer_value] [-summary] [-eval] [-migrate]
```

Parameters

Table A-43 rhpctl query job Command Parameters

Parameter	Description
<code>-jobid <i>job_id</i></code>	Optionally, you can specify the job ID value for the job you want to query. The job ID is obtained while scheduling the job. If you choose this parameter, then the only other option you can specify is <code>-summary</code> . If you do not choose this parameter, then all jobs are queried.
<code>-status {EXECUTED TIMER_RUNNING EXECUTING UNKNOWN TERMINATED }</code>	Optionally, you can specify any of the following states of a job that you want to query: <ul style="list-style-type: none"> • EXECUTED: The job is complete. • TIMER_RUNNING: The timer for the job is still running. • EXECUTING: The timer for the job has expired and is running. • UNKNOWN: There is an unexpected failure due to issues such as a target going down, nodes going down, or any resource failures. • TERMINATED: There is an abrupt failure or the operation has stopped.
<code>-client <i>client_namek</i></code>	Optionally, you can specify the name of a client cluster for which you want to query jobs.
<code>-user <i>user_name</i></code>	Optionally, you can specify the user name of the user for whom a software home is being provisioned.
<code>-since <i>timer_value</i></code>	Optionally, you can specify a date from which to query the jobs, in ISO-8601 format, as in the following example: 2018-07-25T19:13:17+05
<code>-summary</code>	Optionally, you can use this parameter to return only job details.
<code>-eval</code>	Optionally, you can use this parameter to query only evaluation jobs.
<code>-migrate</code>	Optionally, you can use this parameter to query only migration jobs.

Usage Notes

You must run this command on the Fleet Patching and Provisioning Server.

Example

To query a specified scheduled job:

```
$ rhpctl query job -jobid 1
```

This command returns output similar to the following:

```
Job ID: 1
User: fred
Client: fredlinux4
Scheduled job command: "rhpctl import image -image DB-Image1
```

```

-imagetype ORACLEDBSOFTWARE -path /ade/fred_linux4/esw1 -schedule
2018-07-27T13:38:57Z"
Scheduled job execution start time: 2018-07-27T05:38:57-08. Equivalent
local time: 2018-07-27 05:38:57
Current status: EXECUTED
Result file path: "/scratch/rhp_storage/chkbase/scheduled/
job-1-2017-11-27-05:39:14.log"
Job execution start time: 2018-07-27 05:39:14
Job execution end time: 2018-07-27 05:43:09
Job execution elapsed time: 3 minutes 55 seconds

Result file "/scratch/rhp_storage/chkbase/scheduled/
job-1-2018-07-27-05:39:14.log" contents:
slc05amw.foo.com: Audit ID: 4
slc05amw.foo.com: Creating a new ACFS file system for image "DB-
Image1" ...
slc05amw.foo.com: Copying files...
slc05amw.foo.com: Copying home contents...
slc05amw.foo.com: Changing the home ownership to user fred...
slc05amw.foo.com: Changing the home ownership to user fred...

```

rhpcctl collect osconfig

Collects a backup of the operating system configuration for a cluster.

Syntax

```

rhpcctl collect osconfig -client cluster_name [-targetnode node_name
{-sudouser sudo_user_name -sudopath sudo_binary_location | -root}]

```

Parameters

Table A-44 rhpcctl collect osconfig Command Parameters

Parameter	Description
-client <i>cluster_name</i>	Specify the name of the client cluster.
-targetnode <i>node_name</i>	Optionally, you can specify the name of a particular node in a cluster from which to collect configuration information.
-sudouser <i>sudo_user_name</i> -sudopath <i>sudo_binary_path</i> - root]	If you use the -targetnode parameter, then you must specify either sudo or root to perform super user operations.

rhpcctl compare osconfig

Compares operating system configurations for a specific cluster.

Syntax

```
rhpctl compare osconfig -client cluster_name -node node_name -id1
identifier -id2 identifier
```

Parameters

Table A-45 rhpctl compare osconfig Command Parameters

Parameter	Description
-client <i>cluster_name</i>	Specify the name of the client cluster in which you want to compare operating system configurations.
-node <i>node_name</i>	Specify the name of a node in a remote cluster.
-id1 <i>identifier</i>	Specify an identifier of an operating system configuration to be considered as a reference.
-id2 <i>identifier</i>	Specify an identifier of an operating system configuration to be compared.

rhpctl disable osconfig

Disables a scheduled backup of the operating system configuration and gives the option to delete all collected configuration backups.

Syntax

```
rhpctl disable osconfig [-client cluster_name] [-clean]
```

Usage Notes

- Optionally, you can specify a client cluster name on which you want to disable collection of operating system configuration information.
- Optionally, you can use the `-clean` parameter to delete all operating system configuration backups.

rhpctl enable osconfig

Enable operating system configuration information collection for the client cluster.

Syntax

```
rhpctl enable osconfig -client cluster_name [-retaincopies count]
  [-start timer_value] [-frequency collect_frequency] [-collectnow
  [-targetnode node_name {-sudouser sudo_user_name -sudopath
  sudo_binary_location
  | -root}]] [-force]
```

Parameters

Table A-46 rhpctl enable osconfig Command Parameters

Parameter	Description
<code>-client <i>cluster_name</i></code>	Specify the name of the client cluster.
<code>-retaincopies <i>count</i></code>	Optionally, you can specify the number of scheduled backups you want to be maintained. The default value is 37.
<code>-start <i>timer_value</i></code>	Optionally, you can specify a start date and time to run configuration collection according to the following example: 2018-07-23T00:00:00-07
<code>-frequency <i>collect_frequency</i></code>	Optionally, you can specify the configuration collection interval in number of days.
<code>-collectnow</code>	Optionally, you can use this parameter to collect configuration information, immediately.
<code>-targetnode <i>node_name</i></code>	Optionally, you can specify the name of a particular node in a cluster from which to collect configuration information.
<code>-sudouser <i>sudo_user_name</i></code> <code>-sudopath <i>sudo_binary_path</i> -root]</code>	If you use the <code>-targetnode</code> parameter, then you must specify either <code>sudo</code> or <code>root</code> to perform super user operations.
<code>-force</code>	Optionally, you can use this parameter to forcibly modify the count for the <code>-retaincopies</code> parameter previously set.

rhpctl query osconfig

Provides historic operating system configuration collection information, such as the collection schedule, retention count, scheduled job for periodic collection, and collection data.

Syntax

```
rhpctl query osconfig -client client_name
```

Usage Notes

Provide the name of the client cluster that you want to query operating system configuration collection information.

Example

This command returns output similar to the following:

```
$ rhpctl query osconfig -client rhpdemocluster

OSConfig Enabled: true
Collection start time: "00:00:00"
Collection frequency: "1"
retaincopies count: "35"
OSConfig periodic Job ID: "38"
```

```
Collection storage path: "/scratch/rhp_storage/chkbase/osconfig/
rhpdemocluster"
Latest list of nodes for collections : "mjk00fwc"
OSConfig ID: "22" Collected on: "Jul 27, 2018 22:00:58 PM"
OSConfig ID: "21" Collected on: "Jul 26, 2018 22:00:47 PM"
OSConfig ID: "20" Collected on: "Jul 25, 2018 22:00:29 PM"
```

rhpctl query peerserver

Displays information for a registered peer Fleet Patching and Provisioning Server.

Syntax

```
rhpctl query peerserver [-server server_cluster_name [-serverPolicy]]
```

Parameters

Table A-47 rhpctl query peerserver Command Parameters

Parameter	Description
-server <i>server_cluster_name</i>	Optionally, you can specify the name of the Fleet Patching and Provisioning Server cluster for which you want to view the information.
-serverPolicy	Optionally, you can specify the image policy for the peer Fleet Patching and Provisioning Server for which you want to view the information.

rhpctl add role

Creates roles and adds them to the list of existing roles on the Fleet Patching and Provisioning Server configuration.



See Also:

[Fleet Patching and Provisioning Roles](#)

Syntax

```
rhpctl add role -role role_name -hasRoles roles
```

Parameters

Table A-48 rhpctl add role Command Parameters

Parameter	Description
-role <i>role_name</i>	Specify a name for the role that you want to create.

Table A-48 (Cont.) rhpctl add role Command Parameters

Parameter	Description
<code>-hasRoles roles</code>	Specify a comma-delimited list of roles to include with the new role. GH_ROLE_ADMIN GH_AUDIT_ADMIN GH_USER_ADMIN GH_SITE_ADMIN GH_WC_ADMIN GH_WC_OPER GH_WC_USER GH_IMG_ADMIN GH_IMG_USER GH_SUBSCRIBE_USER GH_SUBSCRIBE_ADMIN GH_IMGTYPE_ADMIN GH_IMGTYPE_ALLOW GH_IMGTYPE_OPER GH_SERIES_ADMIN GH_SERIES_CONTRIB GH_IMG_TESTABLE GH_IMG_RESTRICT GH_IMG_PUBLISH GH_IMG_VISIBILITY GH_JOB_USER GH_JOB_ADMIN GH_AUTHENTICATED_USER GH_CLIENT_ACCESS GH_ROOT_UA_CREATE GH_ROOT_UA_ASSOCIATE GH_ROOT_UA_USE GH_OPER GH_CA GH_SA OTHER

Usage Notes

- You can only run this command on the Fleet Patching and Provisioning Server.
- You must be assigned the GH_ROLE_ADMIN role to run this command.

Example

To add a role on the Fleet Patching and Provisioning Server:

```
$ rhpctl add role -role hr_admin -hasRoles GH_WC_USER,GH_IMG_USER
```

rhpcctl delete role

Deletes a role from the list of existing roles on the Fleet Patching and Provisioning Server configuration.

Syntax

```
rhpcctl delete role -role role_name
```

Usage Notes

- Specify the name of the role that you want to delete
- You *cannot* delete any built-in roles
- You can only run this command on the Fleet Patching and Provisioning Server

Example

To delete a role from the Fleet Patching and Provisioning Server:

```
$ rhpcctl delete role -role hr_admin
```

rhpcctl grant role

Grants a role to a client user or to another role.

Syntax

```
rhpcctl grant role {-role role_name {-user user_name [-client  
cluster_name]  
| -grantee role_name}} | {[-client cluster_name]  
[-maproles role=user_name[+user_name...]  
[,role=user_name[+user_name...][, ...]}
```

Parameters

Table A-49 rhpcctl grant role Command Parameters

Parameter	Description
-role <i>role_name</i>	Specify the name of the role that you want to grant clients or users.
-user <i>user_name</i> [-client <i>cluster_name</i>]	Specify the name of a user. The user name that you specify must be in the form of <i>user@rhpcclient</i> , where <i>rhpcclient</i> is the name of the Fleet Patching and Provisioning Client. Optionally, you can specify the name of the client cluster to which the user belongs.
-grantee <i>role_name</i>	Use this parameter to specify a role to which you want to grant another role.

Table A-49 (Cont.) rhpctl grant role Command Parameters

Parameter	Description
<code>[-client cluster_name] -maproles</code>	You can map either built-in roles or roles that you have defined to either users on a specific client cluster or to specific users.
<code>role=user_name[+user_name...]</code>	When you use the <code>-maproles</code> parameter, use a plus sign (+) to map more than one user to a specific role. Separate additional role/user pairs with commas.
<code>[,role=user_name[+user_name...]][,...]</code>	

Note:

Starting with Oracle Grid Infrastructure 21c, the `-maproles` parameter is deprecated. This parameter can be desupported in a future release.

Example

The following example grants a role, ABC, to four specific users.

```
$ rhpctl grant role -role ABC -maproles
ABC=mjk@rhpc1+dc@rhpc1+aj@rhpc1+jc@rhpc1
```

rhpctl query role

Displays the configuration information of a specific role.

Syntax

```
rhpctl query role [-role role_name]
```

Usage Notes

- Specify the name of the role for which you want to display the configuration information
- You can only run this command on the Fleet Patching and Provisioning Server

Example

This command returns output similar to the following:

```
$ rhpctl query role -role GH_CA

Role name: GH_CA
Associated roles: GH_IMGTYPE_ADMIN, GH_IMGTYPE_ALLOW, GH_IMGTYPE_OPER,
GH_IMG_ADMIN,
GH_IMG_PUBLISH, GH_IMG_RESTRICT, GH_IMG_TESTABLE, GH_IMG_VISIBILITY,
GH_SERIES_ADMIN,
```

GH_SERIES_CONTRIB, GH_SUBSCRIBE_ADMIN, GH_WC_ADMIN
Users with this role: rhpusr@rwsdcVM13

rhpcctl revoke role

Revokes a role from a client user.

Syntax

```
rhpcctl revoke role {-role role_name {-user user_name
  [-client cluster_name] | -grantee role_name}}
  | {[ -client cluster_name] -maproles role=user_name[+user_name...]
  [,role=user_name[+user_name...]...]}
```

Parameters

Table A-50 rhpcctl revoke role Command Parameters

Parameter	Description
-role <i>role_name</i>	Specify the name of the role from which you want to revoke clients or users.
-user <i>user_name</i> [-client <i>cluster_name</i>]	Specify the name of a user and, optionally, a client cluster from which you want to revoke a role. The user name that you specify must be in the form of <i>user@rhpcclient</i> , where <i>rhpcclient</i> is the name of the Fleet Patching and Provisioning Client.
-grantee <i>role_name</i>	Specify the grantee role name.
[-client <i>client_name</i>] -maproles <i>role=user_name</i> [+ <i>user_name</i> ...]	You can map either built-in roles or roles that you have defined to specific users. Use a plus sign (+) to map more than one user to a specific role. Separate additional role/user pairs with commas. Optionally, you can also specify a client cluster.

Note:

Starting with Oracle Grid Infrastructure 21c, the `-maproles` parameter is deprecated. This parameter can be desupported in a future release.

rhpcctl add series

Adds a series to the Fleet Patching and Provisioning Server configuration.

Syntax

```
rhpcctl add series -series series_name [-image image_name]
```

Parameters

Table A-51 rhpctl add series Command Parameters

Parameter	Description
<code>-series <i>series_name</i></code>	Specify a name for the series that you want to add.
<code>-image <i>image_name</i></code>	Optionally, you can specify the name of a configured image. This image becomes the first in the series.

Example

To add a series:

```
$ rhpctl add series -series DB12_series
```

rhpctl delete series

Deletes a series from the Fleet Patching and Provisioning Server configuration.

Syntax

```
rhpctl delete series -series series_name [-force]
```

Usage Notes

- Specify the name of the series that you want to delete.
- Use `-force` to delete an image series even if the series includes images.
- Before deleting an image series, you must first remove all images from the series by using the [rhpctl deleteimage series](#) command.
- This command *does not* delete images, only series.

Example

The following example deletes a series called PRODDBSERIES:

```
$ rhpctl delete series -series PRODDBSERIES
```

rhpctl deleteimage series

Deletes an image from a series.

Syntax

```
rhpctl deleteimage series -series series_name -image image_name
```

Parameters

Table A-52 rhpctl deleteimage series Command Parameters

Parameter	Description
<code>-series <i>series_name</i></code>	Specify the name of the series from which you want to delete an image.
<code>-image <i>image_name</i></code>	Specify the name of the image that you want to delete from a series.

Example

The following command deletes an image called PRODIMAGEV0 from a series called PRODDBSERIES:

```
$ rhpctl deleteimage series -series PRODDBSERIES -image PRODIMAGEV0
```

rhpctl insertimage series

Inserts an existing image into a series.

**Note:**

A single image can belong to one or more series.

Syntax

```
rhpctl insertimage series -series series_name -image image_name
[-before image_name]
```

Parameters

Table A-53 rhpctl insertimage series Command Parameters

Parameter	Description
<code>-series <i>series_name</i></code>	Specify the name of the series into which you want to insert an image.
<code>-image <i>image_name</i></code>	Specify the name of the image that you want to insert into a series.
<code>-before <i>image_name</i></code>	Optionally, you can specify the name of an image before which you want to insert the new image.

Example

To insert an image into a series:

```
rhpcctl insertimage series -series DB12_series -image DB12102_PSU
```

rhpcctl query series

Displays the configuration of a series.

Syntax

```
rhpcctl query series [-series series_name | -image image_name]  
[-server server_cluster_name] [-rhpsserver rhps_regex]
```

Parameters**Table A-54 rhpcctl query series Command Parameters**

Parameter	Description
-series <i>series_name</i>	Specify the name of the series for which you want to display the configuration.
-image <i>image_name</i>	Alternatively, you can specify the name of a configured image.
-server <i>server_cluster_name</i>	Specify the name of the server cluster to which the image corresponds.
-rhpsserver <i>rhps_regex</i>	Specify a regular expression to match the cluster name of the servers where the operation must be executed.

Usage Notes

If you do not specify a series or an image by name, then CRSCCTL returns information for all series.

The `-rhpsserver` parameter indicates where the operation should be executed and `-server` indicates who the operation should be about. When `-rhpsserver` is used, the command is executed on the servers whose name matches the regular expression provided. When `-server` is used, the command will be about the server provided. For example:

- The following command executes locally and lists the series that have been replicated to `peerA`

```
rhpcctl query series -server peerA
```

- The following command executes on `peerA` and lists the series have been configured on `peerA`

```
rhpcctl query series -rhpsserver peerA
```

- The following command executes on all servers and lists the series that each server has replicated on `peerA`

```
rhpctl query series -server peerA -rhpserver .+'

```

When issuing a command for a peer server using the `-rhpserver` option, the user running the command must be an existing user of the peer server and the user must have a required role. To enable a user from a peer server to run commands on the local server, run the `rhpctl grant role` command to grant a required role to the peer server user and to specify the cluster name of the peer server to which the user belongs. For example:

```
$ rhpctl grant role -role role_name -user user_name -client cluster_name

```

To add multiple users, run the following command:

```
$ rhpctl grant role -client cluster_name -maproles
role=user_name[+user_name...][,role=user_name[+user_name...]]...

```

For information about granting roles with RHPCTL, refer to [rhpctl grant role](#)

Example

This command returns output similar to the following:

```
$ rhpctl query series

Image series: DB12_series
Image series: GRID_series
Image series: DB112_series

```

rhpctl subscribe series

Subscribes a specific user to an image series.

Syntax

```
rhpctl subscribe series -series series_name [-user user_name [-client
cluster_name]]

```

Parameters

Table A-55 rhpctl subscribe series Command Parameters

Parameter	Description
<code>-series series_name</code>	Specify the image series to which you want to subscribe a user.
<code>-user user_name</code>	Specify an operating system user to whom you are subscribing the image series.
<code>-client cluster_name</code>	Optionally, you can specify the name of the client cluster to which the operating system user belongs.

rhpcctl unsubscribe series

Unsubscribes a user from an image series.

Syntax

```
rhpcctl unsubscribe series -series series_name [-user user_name [-client cluster_name]]
```

Parameters

Table A-56 rhpcctl unsubscribe series Command Parameters

Parameter	Description
-series <i>series_name</i>	Specify the image series from which you want to unsubscribe a user.
-user <i>user_name</i>	Specify an operating system user from whom you are unsubscribing the image series.
-client <i>cluster_name</i>	Optionally, you can specify the name of the client cluster to which the operating system user belongs.

rhpcctl export server

Exports data from the repository to a Fleet Patching and Provisioning Server data file.

Syntax

```
rhpcctl export server -server peer_server_name -serverdata file_path
```

Usage Notes

- Specify the name of a peer server cluster.
- Specify the path to the file containing the Fleet Patching and Provisioning Server data.

rhpcctl query server

Displays the configuration of a server.

Syntax

```
rhpcctl query server
```

Usage Notes

This command has no parameters.

Example

This command displays output similar to the following:

```
$ ./rhpctl query server
```

```
Fleet Patching and Provisioning Server (RHPS): rhps-myserver
Storage base path: /u01/app/RHPImages
Disk Groups: RHPDATA
Port number: 8896
```

rhpctl register server

Registers the specific Fleet Patching and Provisioning Server as a peer server.

Syntax

```
rhpctl register server -server server_cluster_name -serverdata file
    {-root | -cred cred_name | -sudouser sudo_username -sudopath
    path_to_sudo_binary
    | -auth plugin_name [-arg1 name1:value1 [-arg2 name2:value2 ...]]}
```

Parameters

Table A-57 rhpctl register server Command Parameters

Parameter	Description
-server <i>server_cluster_name</i>	Specify the name of the Fleet Patching and Provisioning Server cluster that you want to register.
-serverdata <i>file</i>	Specify the path to the file containing the Fleet Patching and Provisioning Server data.
-root - cred <i>cred_name</i> -sudouser <i>sudo_username</i> -sudopath <i>sudo_binary_location</i> -auth <i>plugin_name</i> <i>plugin_args</i>	Choose -root to perform super user operations as root. Alternatively, you can choose either to specify a credential name to associate the user name and password credentials to access a remote node, to perform super user operations as a sudo user by specifying a sudo user name and the path to the sudo binary, or to use an authentication plugin to access the remote node.

rhpctl unregister server

Unregisters a specific Fleet Patching and Provisioning Server as a peer server.

Syntax

```
rhpctl unregister server -server server_cluster_name
```

Usage Notes

Specify the name of the Fleet Patching and Provisioning Server you want to unregister as a peer.

rhpcctl delete user

Deletes a user from the Fleet Patching and Provisioning repository.

Syntax

```
rhpcctl delete user -user user_name [-client cluster_name]
```

Parameters

Table A-58 rhpcctl delete user Command Parameters

Parameter	Description
-user <i>user_name</i>	Specify the name of the user you want to delete from a Fleet Patching and Provisioning Client.
-client <i>cluster_name</i>	Optionally, you can specify the name of the client cluster from which you want to delete from a specific user.

Usage Notes

- You can delete non built-in users only if that user does not own any working copies.
- If the user created an image or image series, then you can still delete the user, but the creator of the image or image series is changed to *internal-user@GHS*.
- If the user was the owner of an image series, then you can delete the user, but the owner of the image series will be changed to *internal-user@GHS*. You can still use the affected image series as normal, such that you can still provision a working copy from the affected image series, and you can still insert or delete images from the affected image series.

Example

The following example deletes the user named `scott` on the server cluster from the Fleet Patching and Provisioning repository:

```
$ rhpcctl delete user -user scott
```

rhpcctl modify user

Modifies the email address of a specific user.

Syntax

```
rhpcctl modify user -user user_name -email email_address [-client client_name]
```

Parameters

Table A-59 rhpctl modify user Command Parameters

Parameter	Description
<code>-user <i>user_name</i></code>	Specify an operating system user whose email address you want to modify.
<code>-email <i>email_address</i></code>	Specify the email address of the operating system user in the RFC 822 format.
<code>-client <i>client_name</i></code>	Optionally, you can specify the name of the client cluster to which the operating system user belongs.

rhpctl register user

Registers an email address for a specific user.

Syntax

```
rhpctl register user -user user_name -email email_address [-client client_name]
```

Parameters

Table A-60 rhpctl register user Command Parameters

Parameter	Description
<code>-user <i>user_name</i></code>	Specify an operating system user whose email address you want to register.
<code>-email <i>email_address</i></code>	Specify the email address of the operating system user in the RFC 822 format.
<code>-client <i>client_name</i></code>	Optionally, if you run the command on the Fleet Patching and Provisioning Server, then you can specify the name of the client cluster to which the operating system user belongs. Otherwise, the command applies to a user on the cluster (either the Fleet Patching and Provisioning Server or Client) where the command is run.

Example

An example of this command is:

```
$ rhpctl register user -user scott -email scott@company.com
```

rhpctl unregister user

Unregisters an email address for a specific user.

Syntax

```
rhpcctl unregister user -user user_name [-client client_name]
```

Parameters

Table A-61 rhpcctl unregister user Command Parameters

Parameter	Description
-user <i>user_name</i>	Specify an operating system user whose email address you want to unregister.
-client <i>client_name</i>	Optionally, you can specify the name of the client cluster to which the operating system user belongs.

rhpcctl add useraction

Configures a user action and its associated script and action file.

Syntax

```
rhpcctl add useraction -useraction user_action_name -actionscrip
script_name
  [-actionfile file_name]
  [-pre | -post] [-optype option] [-phase operation_phase]
  [-onerror {ABORT | CONTINUE}]
  [-runscope {ONENODE | ALLNODES | AUTO | FIRSTNODEONRHPS |
LASTNODEONRHPS | ALLNODESONRHPS}]
  [-runasroot] [-runninginstance]
```

Parameters

Table A-62 rhpcctl add useraction Command Parameters

Parameter	Description
-useraction <i>user_action_name</i>	Specify the name of the user action you want to add.
-actionscrip <i>script_name</i>	Associate a specific action script to run with the user action.
-actionfile <i>file_name</i>	Optionally, you can specify an action file that is required by the user action.
-pre -post	Use the -pre parameter to run the user action before the add operation or the -post parameter to run the user action after.

Table A-62 (Cont.) rhpctl add useraction Command Parameters

Parameter	Description
-optype <i>option</i>	<p>Optionally, you can specify the operation for which the user action is configured. Options include:</p> <ul style="list-style-type: none"> IMPORT_IMAGE ADD_WORKINGCOPY DELETE_WORKINGCOPY ADD_DATABASE DELETE_DATABASE MOVE_DATABASE ADD_PDB_DATABASE DELETE_PDB_DATABASE MOVE_GIHOME UPGRADE_DATABASE UPGRADE_GIHOME ADDNODE_GIHOME DELETENODE_GIHOME ADDNODE_DATABASE DELETENODE_DATABASE ADDNODE_WORKINGCOPY ZDTUPGRADE_DATABASE ZDTUPGRADE_DATABASE_SNAPDB ZDTUPGRADE_DATABASE_DBUA ZDTUPGRADE_DATABASE_SWITCHBACK MIGRATE_DATABASE UPDATE_EXADATA
-phase	Specify the phase of the operation for which the user action is configured.
-onerror {ABORT CONTINUE}	Optionally, you can choose whether to abort or continue the operation if the user action encounters an error while it is running.
-runscope {ONENODE ALLNODES AUTO FIRSTNODEONRHPS LASTNODEONRHPS ALLNODESONRHPS}	<p>Optionally, you can specify the nodes where the user action is run. Choose ONENODE to run the user action for each database on the node on which a patch was applied to the database. Choose ALLNODES to run the user action for each database on every cluster node. Choose AUTO for a run scope based on the other command options.</p> <p>Specify FIRSTNODEONRHPS, LASTNODEONRHPS, or ALLNODESONRHPS to run the user action script on FPPS when the operation is performed on first node or last node or all nodes.</p>
-runasroot	Run the rhpctl add useraction command as root user.
-runninginstance	Specify this parameter to run the user action only on the nodes that have a running database instance. You can use this parameter only with the MOVE_DATABASE, MOVE_GIHOME, and UPGRADE_DATABASE operation types.

rhpctl delete useraction

Deletes an existing user action configuration.

Syntax

```
rhpcctl delete useraction -useraction user_action_name
```

Usage Notes

Specify the name of a user action you want to delete.

rhpcctl modify useraction

Modifies the configuration of the specified user action name.

Syntax

```
rhpcctl modify useraction -useraction user_action_name [-actionscript
script_name]
  [-actionfile file_name] [-pre | -post] [-optype option]
  [-onerror {ABORT | CONTINUE}] [-runscope {ONENODE | ALLNODES | AUTO |
FIRSTNODEONRHPS | LASTNODEONRHPS | ALLNODESONRHPS}] [-runninginstance]
```

Parameters**Table A-63 rhpcctl modify useraction Command Parameters**

Parameter	Description
-useraction <i>user_action_name</i>	Specify the name of the user action you want to modify.
-actionscript <i>script_name</i>	Optionally, you can specify an action script to run.
-pre -post	Use the -pre parameter to run the user action before the modify operation or the -post parameter to run the user action after.

Table A-63 (Cont.) rhpctl modify useraction Command Parameters

Parameter	Description
-o <code>type option</code>	<p>Optionally, you can specify the operation for which the user action is configured. Options include:</p> <ul style="list-style-type: none"> IMPORT_IMAGE ADD_WORKINGCOPY DELETE_WORKINGCOPY ADD_DATABASE DELETE_DATABASE MOVE_DATABASE ADD_PDB_DATABASE DELETE_PDB_DATABASE MOVE_GIHOME UPGRADE_DATABASE UPGRADE_GIHOME ADDNODE_GIHOME DELETENODE_GIHOME ADDNODE_DATABASE DELETENODE_DATABASE ADDNODE_WORKINGCOPY ZDTUPGRADE_DATABASE ZDTUPGRADE_DATABASE_SNAPDB ZDTUPGRADE_DATABASE_DBUA ZDTUPGRADE_DATABASE_SWITCHBACK MIGRATE_DATABASE UPDATE_EXADATA
-onerror {ABORT CONTINUE}	Optionally, you can choose whether to abort or continue the operation if the user action encounters an error while it is running.
-runscope {ONENODE ALLNODES AUTO FIRSTNODEONRHPS LASTNODEONRHPS ALLNODESONRHPS}	<p>Optionally, you can specify the nodes where the user action is run. Choose ONENODE to run the user action for each database on the node on which a patch was applied to the database. Choose ALLNODES to run the user action for each database on every cluster node. Choose AUTO for a run scope based on the other command options.</p> <p>Specify FIRSTNODEONRHPS, LASTNODEONRHPS, or ALLNODESONRHPS to run the user action script on FPPS when the operation is performed on first node or last node or all nodes.</p>
-runninginstance	Specify this parameter to run the user action only on the nodes that have a running database instance. You can use this parameter only with the MOVE_DATABASE, MOVE_GIHOME, and UPGRADE_DATABASE operation types.

rhpctl query useraction

Displays the configuration of a user action.

Syntax

```
rhctl query useraction [-useraction user_action_name | -imagetype
image_type]
    [-optype option]
```

Parameters

Table A-64 rhctl query useraction Command Parameters

Parameter	Description
-useraction <i>user_action_name</i>	Specify the name of the user action you want to query.
-imagetype <i>image_type</i>	Alternatively, you can specify the software type. Use ORACLEDBSOFTWARE (default) for Oracle database software, ORACLEGISoftware for Oracle Grid Infrastructure software, and SOFTWARE for all other software. For a custom image type, use the image type name.
-optype <i>option</i>	Optionally, you can specify the operation for which to run the query. Options include: IMPORT_IMAGE ADD_WORKINGCOPY DELETE_WORKINGCOPY ADD_DATABASE DELETE_DATABASE MOVE_DATABASE ADD_PDB_DATABASE DELETE_PDB_DATABASE MOVE_GIHOME UPGRADE_DATABASE UPGRADE_GIHOME ADDNODE_GIHOME DELETENODE_GIHOME ADDNODE_DATABASE DELETENODE_DATABASE ADDNODE_WORKINGCOPY ZDTUPGRADE_DATABASE ZDTUPGRADE_DATABASE_SNAPDB ZDTUPGRADE_DATABASE_DBUA ZDTUPGRADE_DATABASE_SWITCHBACK MIGRATE_DATABASE UPDATE_EXADATA

rhctl add workingcopy

Creates a working copy on a client cluster.

Syntax

To add a working copy to a client cluster:

```

rhpctl add workingcopy -workingcopy workingcopy_name
  {-image image_name | -series series_name}
  [-oraclebase oraclebase_path]
  [-path where_path]
  [-localmount [-location <zipped_home_path>]]
  [-storagetype {LOCAL | RHP_MANAGED}]
  [-user user_name]
  [-gimr | -dbname unique_db_name
    [-dbtype {RACONENODE | RAC | SINGLE}] [-datafileDestination
datafileDestination_path]
    [-dbtemplate { file_path | image_name:relative_file_path}]
    {-node node_list |
      -serverpool pool_name [-pqpool pool_name |
      -newpqpool pool_name -pqcardinality cardinality] |
      -newpool pool_name -cardinality cardinality [-pqpool
pool_name |
      -newpqpool pool_name -pqcardinality cardinality]}
    [-cdb] [-pdbName pdb_prefix [-numberOfPDBs pdb_count]]]
  [-client cluster_name] [-ignoreprereq | -fixup]
  [-responsefile response_file_path] [-clusternodes node_list]
  [-groups group_list]
  [-root | -cred cred_name | -sudouser sudo_username
    -sudopath path_to_sudo_binary | -auth plugin_name [-arg1
name1:value1
    [-arg2 name2:value2 ...]]]
  [-notify [-cc users_list]]
  [-asmclientdata data_path]
  [-gnsclientdata data_path] [-clustermanifest data_path] [-
softwareonly]
  [-local] [-inventory inventory_path] [-targetnode target_node_name]
  [-agpath read_write_path -aupath gold_image_path] [-setupssh]
  [-useractiondata user_action_data] [-eval] [-schedule {timer_value |
NOW}]
  [-checkwcpatches -sourcehome source_home_path] [-scan scan_name]
  [-diskDiscoveryString disk_discovery_string] [-readonly]

```

Parameters

Table A-65 rhpctl add workingcopy Command Parameters

Parameter	Description
-workingcopy <i>workingcopy_name</i>	Specify a name for the working copy that you want to create.
{-image <i>image_name</i> - series <i>series_name</i> }	Specify the name of a configured image from which to create a working copy or the name of an image series from which RHPCTL takes the latest image when adding a working copy.

Table A-65 (Cont.) rhpctl add workingcopy Command Parameters

Parameter	Description
-oraclebase <i>oracle_base_path</i>	Specify an ORACLE_BASE path for provisioning an Oracle Database or Oracle Grid Infrastructure home. You can specify either an existing directory or a new directory. Note: This parameter is required only for the ORACLEDBSOFTWARE and ORACLEGISOFTWARE image types.
-inventory <i>inventory_path</i>	Specify the location of the Oracle Inventory directory.
-path <i>absolute_path</i>	Specify the absolute path for provisioning the software home on the client side (this location must be empty). For Oracle Database images, this becomes the ORACLE_HOME. Note: This parameter is required for LOCAL storage types, and is invalid for RHP_MANAGED.
-storagetype {LOCAL RHP_MANAGED}	Specify the type of storage for the software home.
-user <i>user_name</i>	Specify the name of the user that will own the working copy being provisioned. If you do not specify this parameter, then the working copy is owned by the user running the command. If you are provisioning to a remote cluster, then the user name must be a valid user on the remote cluster. The user ID need not be the same between the two clusters, but the user name must exist on both. Note: You cannot use -user simultaneously with the -softwareonly parameter.
-gimr	Perform the operations required for a Grid Infrastructure Management Repository (GIMR) database
-dbname <i>unique_db_name</i>	Specify the unique name of the database (DB_UNIQUE_NAME without DB_DOMAIN) that you are adding.
-dbtype {RACONENODE RAC SINGLE}	Specify whether the database is Oracle RAC One Node, Oracle RAC, or a nonclustered database.
-datafileDestination <i>datafileDestination_path</i>	Specify the data file destination location or the name of the Oracle Automatic Storage Management (Oracle ASM) disk group. Note: You cannot specify a disk group for Oracle Database versions before Oracle Database 11g release 2 (11.2).
-dbtemplate <i>file_path</i> <i>image_name:relative_file_path</i>	Specify the absolute file path to a database template or the relative path to the image home directory on a Fleet Patching and Provisioning Server.
-node <i>node_list</i>	Specify a node or comma-delimited list of several nodes. Enter a node name for a single-instance Oracle home.
-serverpool <i>server_pool_name</i>	Specify the name of an existing server pool.
-newppool <i>server_pool_name</i>	Optionally, you can create a new server pool to be used for parallel queries. Specify a name for the new server pool. Note: This parameter is only applicable in an Oracle Flex Cluster environment because it refers to server pools running on non-Hub Nodes.
-newpool <i>server_pool_name</i>	Optionally, you can create a new server pool. Specify a name for the new server pool.

Table A-65 (Cont.) rhpctl add workingcopy Command Parameters

Parameter	Description
<code>-pqcardinality cardinality</code>	If you create a new server pool, then you must specify a cardinality value for the server pool. Note: This parameter is only applicable in an Oracle Flex Cluster environment.
<code>-cardinality cardinality</code>	If you create a new server pool, then you must specify a cardinality value for the server pool.
<code>-cdb</code>	Optionally, use this parameter to create a database as a container database.
<code>-pdbName pdb_prefix</code>	If you are creating one or more pluggable databases, then specify a pluggable database name prefix.
<code>-numberOfPDBs pdb_count</code>	Specify the number of pluggable databases you want to create.
<code>-client cluster_name</code>	Specify the name of the client cluster.
<code>-ignoreprereq -fixup</code>	You can choose to ignore the Clusterware Verification Utility (CVU) checks or you can choose to run the recommended fixup script. Note: These parameters are valid only when you are provisioning Oracle Grid Infrastructure.
<code>-responsefile response_file_path</code>	Specify a response file to use when you provision Oracle Grid Infrastructure.
<code>-clusternodes node_name:node_vip[:node _role] [,node_name:node_vip[:no de_role]...]</code>	Specify a comma-delimited list of cluster node information on which to provision Oracle Clusterware.
<code>-groups "OSDBA OSOPER OSASM OSBACKUP OSDG OSKM OSRAC=group_name[,...]"</code>	Specify a comma-delimited list of Oracle groups, enclosed in double quotation marks (" "), that you want to configure in the working copy. For example: <code>-groups "OSDBA=dba,OSOPER=oper"</code>
	When you create a gold image from a source home or working copy, the gold image inherits the groups configured in the source. When you create a working copy from that gold image using <code>rhpctl add workingcopy</code> , by default, the new working copy inherits the same groups as the gold image. If you use the <code>-groups</code> parameter on the command line, then: <ul style="list-style-type: none"> Groups configured in the gold image that you do not specify on the command line are inherited by the working copy. Groups configured in the gold image that you also specify on the command line are set to the value that you specify on the command line (command line parameters override the gold image). Groups that you specify on the command line that are not in the gold image are added to the configured groups in the gold image (the command line adds new groups). Notes: <ul style="list-style-type: none"> When you move or upgrade a source home (unmanaged or working copy), the groups in the destination working copy must match those of the source home. You cannot use <code>-groups</code> simultaneously with the <code>-softwareonly</code> parameter.

Table A-65 (Cont.) rhpctl add workingcopy Command Parameters

Parameter	Description
<code>-root</code> <code>-cred cred_name</code> <code>-sudouser sudo_user_name</code> <code>-sudopath sudo_binary_location</code> <code>-auth plugin_name</code> <code>plugin_args</code>	If you choose to use the <code>-targetnode</code> parameter, then you must choose either <code>root</code> , a credential name, <code>sudo</code> , or an authentication plugin to access the remote node. Choose <code>-root</code> to perform super user operations as <code>root</code> . Alternatively, you can choose either to specify a credential name to associate the user name and password credentials to access a remote node, to perform super user operations as a <code>sudo</code> user by specifying a <code>sudo</code> user name and the path to the <code>sudo</code> binary, or to use an authentication plugin to access the remote node.
<code>-notify [-cc user_list]</code>	Specify this parameter to have email notifications sent to the owner of the working copy. Optionally, you can include a list of additional users who will receive notifications.
<code>-asmclientdata data_path</code>	Specify the path to a file that contains Oracle ASM client data.
<code>-gnsclientdata data_path</code>	Specify the path to a file that contains the Grid Naming Service (GNS) data.
<code>-clustermanifest data_path</code>	Optionally, you can specify the location of cluster manifest file. You can use this parameter when the Fleet Patching and Provisioning Server is on a domain services cluster and you are creating a member cluster.
<code>-local</code>	Use this parameter to provision only Oracle Grid Infrastructure software on the local node. Note: You can only use this parameter in conjunction with the <code>-softwareonly</code> parameter, and only when running the <code>rhpctl add workingcopy</code> command on a Fleet Patching and Provisioning Server.
<code>-softwareonly</code>	Use this parameter to provision only Oracle Grid Infrastructure software.
<code>-targetnode target_node_name</code>	Specify the name of a node in a remote cluster with no Fleet Patching and Provisioning Client on which you want to provision a working copy.
<code>-agpath read_write_path</code> <code>-aupath gold_image_path</code>	Use <code>-agpath</code> to specify the path to the read-write, site-specific configuration changes to set the persistent home path, and use <code>-aupath</code> to specify the path for the read-only gold image to set the persistent home path.
<code>-setupssh</code>	Use this parameter to set up passwordless SSH user equivalence on the remote nodes for the provisioning user.
<code>-useractiondata user_action_data</code>	Optionally, you can pass a value to the <code>useractiondata</code> parameter of the user action script.
<code>-eval</code>	Optionally, you can use this parameter to evaluate the impact of this command on the system without actually running the command.
<code>-schedule {timer_value NOW}</code>	Optionally, you can use this parameter to schedule a time to run this operation, in ISO-8601 format, as in the following example: 2018-07-25T19:13:17+05 If <code>NOW</code> is specified, then the job is scheduled immediately.
<code>-checkwcpatches</code> <code>-sourcehome source_home_path</code>	Optionally, you can use the <code>-checkwcpatches</code> and <code>-sourcehome</code> parameters to compare patches in a specific source home path with the patches in the working copy you want to add.
<code>-scan scan_name</code>	Optionally, you can use this parameter to specify a SCAN name.
<code>-diskDiscoveryString disk_discovery_string</code>	Optionally, you can use this parameter to specify a disk discovery string.

Table A-65 (Cont.) rhpctl add workingcopy Command Parameters

Parameter	Description
-readonly	Optionally, you can use this parameter to add the database working copy as a read-only home.

Usage Notes



Note:

Member Clusters, which are part of the Oracle Cluster Domain architecture, are desupported in Oracle Grid Infrastructure 21c.



Note:

Domain Services Cluster (DSC), which is part of the Oracle Cluster Domain architecture, is deprecated in Oracle Grid Infrastructure 21c and can be desupported in a future release.

- You can obtain context sensitive help for specific use cases for the `rhpctl add workingcopy` command, as follows:

```
$ rhpctl add workingcopy -help [REMOTEPROVISIONING | STORAGETYPE |
ADMINDB
| GRIDHOMEPROV | SWONLYGRIDHOMEPROV | STANDALONEPROVISIONING |
GGHOMEPROVISIONING]
```

- If you choose to use the `-schedule` parameter, then you must run this command on the Fleet Patching and Provisioning Server.

Examples

- To create a working copy on a client cluster for yourself or another user:

```
rhpctl add workingcopy -workingcopy workingcopy_name {-image image_name |
-series series_name} -oraclebase oracle_base_path -client cluster_name
[-user user_name]
```

- To create a working copy on storage that you specify:

```
rhpctl add workingcopy -workingcopy workingcopy_name {-image image_name |
-series series_name} -oraclebase oracle_base_path -storagetype
{LOCAL | RHP_MANAGED} [-path absolute_path]
```

- To create and configure a working copy of Oracle Grid Infrastructure:

```
rhptcl add workingcopy -workingcopy workingcopy_name {-image image_name |
  -series series_name} {-root | -cred cred_name | -sudouser sudo_user_name
  -sudopath sudo_binary_path} -responsefile response_file_path
  [-clusternodes node_information] [-user user_name] [-oraclebase
  oracle_base_path]
  [-path absolute_path] [-asmclientdata data_path] [-gnsclientdata data_path]
  [-ignoreprereq | -fixup]
```

- To provision a software-only working copy of Oracle Grid Infrastructure:

```
rhptcl add workingcopy -workingcopy workingcopy_name {-image image_name |
  -series series_name} -softwareonly -path Grid_home_path -oraclebase
  oracle_base_path [-local | -client cluster_name]
  [-groups "Oracle_group=user_group[,...]"] [-node client_node_name] |
  {-root | -cred cred_name | -sudouser sudo_user_name -sudopath sudo_binary_path}
  -targetnode node_name]
```

- To provision a working copy on a node or a cluster where Oracle Fleet Patching and Provisioning does not exist:

```
rhptcl add workingcopy -workingcopy workingcopy_name {-image image_name |
  -series series_name} -oraclebase oracle_base_path -user user_name
  -node node_name [-path absolute_path]
  {-root | -cred cred_name | -sudouser sudo_user_name -sudopath sudo_binary_path}
```

Note:

If you are provisioning Oracle database software to a Fleet Patching and Provisioning Client that has been configured with an Oracle ASM disk group, then do not specify the `-path` parameter, so as to enable the Fleet Patching and Provisioning Client to use storage provided by Fleet Patching and Provisioning.

If the Fleet Patching and Provisioning Client is not configured with an Oracle ASM disk group, then specify the `-storagetype` parameter with `LOCAL`, in addition to specifying the `-path` parameter.

rhptcl addnode workingcopy

Extends an Oracle RAC database to another node or nodes in a cluster.

Syntax

```
rhptcl addnode workingcopy -workingcopy workingcopy_name -node node_list
  [-targetnode node_name {-root | -sudouser sudo_username -sudopath
  sudo_binary_path
  | -cred cred_name | -auth plugin_name [-arg1 name1:value1...]} -
  setupssh]
```

```
[-ignoreprereq] [-useractiondata user_action_data] [-eval] [-schedule  
{timer_value | NOW}]
```

Parameters

Table A-66 rhpctl addnode workingcopy Command Parameters

Parameter	Description
-workingcopy <i>workingcopy_name</i>	Specify the name of a working copy that contains the Oracle database you want to extend.
-node <i>node_list</i>	Specify a node or a comma-delimited list of nodes to which you want to extend the database.
-targetnode <i>node_name</i>	Optionally, you can specify a node on which to run this command.
-root -sudouser <i>sudo_username</i>	If you choose to use the -targetnode parameter, then you must choose either sudo or root to access the remote nodes.
-sudopath <i>sudo_binary_path</i> -cred <i>cred_name</i>	If you choose sudo, then you must specify a user name to run super-user operations, and a path to the location of the sudo binary.
-auth <i>plugin_name</i> [-arg1 <i>name1:value1...</i>]	Optionally, you can choose to specify a credential name to associate the user and password credentials to access a remote node. Alternative to -sudouser, -root, or -cred, you can use -auth to specify an authentication plugin to access a remote node.
-ignoreprereq	Use this parameter to ignore the CVU prerequisite checks.
-setupssh	Sets up passwordless SSH user equivalence on the remote nodes for the provisioning user.
-useractiondata <i>user_action_data</i>	Optionally, you can pass a value to the useractiondata parameter of the user action script.
-eval	Optionally, you can use this parameter to evaluate the impact of this command on the system without actually running the command.
-schedule { <i>timer_value</i> NOW}	Optionally, you can schedule a time to run this command in ISO-8601 format. For example: 2018-01-21T19:13:17+05. If NOW is specified, then the job is scheduled immediately.

Usage Notes

- If you are extending a policy-managed database, then the database automatically starts on the new nodes.
- If you are extending an administrator-managed database, then you must also run the rhpctl addnode database command to start the instance.
- If the target cluster is an Oracle Clusterware 11g release 2 (11.2) or 12c release 1 (12.1) cluster, then you must provide either root credentials or provide a sudo user. You must also specify a target node that must be the node name of one of the cluster nodes.

rhpctl delete workingcopy

Deletes an existing working copy.

Syntax

```

rhpctl delete workingcopy -workingcopy workingcopy_name [-notify [-cc
user_list]] [-force]
  [[-targetnode node_name] {-root | -sudouser sudo_user_name -sudopath
  sudo_binary_path -cred cred_name | -auth plugin_name [-arg1
  name1:value1...]}]
  [-useractiondata user_action_data] [-schedule {timer_value | NOW}]

```

Parameters

Table A-67 rhpctl delete workingcopy Command Parameters

Parameter	Description
-workingcopy <i>workingcopy_name</i>	Specify the name of a working copy that you want to delete.
-notify [-cc <i>user_list</i>]	Name of a node in a remote cluster with no Fleet Patching and Provisioning Client.
-targetnode <i>node_name</i>	Optionally, you can specify a particular node from which you want to delete a working copy.
-force	Use this parameter to forcibly delete the database working copy.
-root -sudouser <i>sudo_username</i> -sudopath <i>sudo_binary_path</i> - <i>cred cred_name</i>	<p>If you choose to use the -targetnode parameter, then you must choose either sudo or root to access the remote node.</p> <p>If you choose sudo, then you must specify a user name to run super-user operations, and a path to the location of the sudo binary.</p> <p>Optionally, you can choose to specify a credential name to associate the user and password credentials to access a remote node.</p> <p>Alternative to -sudouser, -root, or -cred, you can use -auth to specify an authentication plugin to access a remote node.</p>
-useractiondata <i>user_action_data</i>	Optionally, you can pass a value to the useractiondata parameter of the user action script.
-schedule { <i>timer_value</i> NOW}	<p>Optionally, you can use this parameter to schedule a time to run this operation, in ISO-8601 format, as in the following example:</p> <p>2018-07-25T19:13:17+05</p> <p>If NOW is specified, then the job is scheduled immediately.</p>

Usage Notes

- This command *will not* delete the working copy if there are any databases configured on it. Use the -force option to override this.
- This command *will not* delete the working copy if there are any running databases on it. The -force option *will not* override this.
- This command *does not* delete the Oracle base that was created when you ran rhpctl add workingcopy.

- If you choose to use the `-schedule` parameter, then you must run this command on the Fleet Patching and Provisioning Server.

Examples

To delete a working copy:

```
$ rhpctl delete workingcopy -workingcopy wcl
```

rhpctl query workingcopy

Displays the configuration information of an existing working copy.

Syntax

```
rhpctl query workingcopy [-workingcopy workingcopy_name [-  
metadataonly] | [-image image_name [-drift]] [-client cluster_name]]  
[-rhpserver rhps_regex]
```

Parameters

Table A-68 rhpctl query workingcopy Command Parameters

Parameter	Description
<code>-workingcopy <i>workingcopy_name</i></code>	Specify the name of a working copy for which you want to display the configuration information.
<code>-metadataonly</code>	Use this parameter only when you use the <code>-workingcopy</code> parameter to query only the metadata of the working copy, which is located in the repository and not run OPatch or connect to the target to query for extra information.
<code>-image <i>image_name</i> [-drift]</code>	Use this parameter to specify the name of a configured image that you want to query. If you specify an image name, then RHPCTL lists all the working copies based on that image. The <code>-drift</code> option lists the bug fixes not included in the golden image.
<code>-client <i>cluster_name</i></code>	Optionally, you can specify a client cluster on which to query working copies.
<code>-rhpserver <i>rhps_regex</i></code>	Specify a regular expression to match the cluster name of the servers where the operation must be executed.

Usage Notes

When issuing a command for a peer server using the `-rhpserver` option, the user running the command must be an existing user of the peer server and the user must have a required role. To enable a user from a peer server to run commands on the local server, run the `rhpctl grant role` command to grant a required role to the peer server user and to specify the cluster name of the peer server to which the user belongs. For example:

```
$ rhpctl grant role -role role_name -user user_name -client cluster_name
```

To add multiple users, run the following command:

```
$ rhpctl grant role -client cluster_name -maproles
role=user_name[+user_name...][,role=user_name[+user_name...]....]
```

For information about granting roles with RHPCTL, refer to [rhpctl grant role](#)

rhpctl update workingcopy

Updates a working copy on a client cluster.

Syntax

```
rhpctl update workingcopy -image image_name -root
    {[-dbnodes dbnode_list]
      [-cells cell_list]
      [-ibswitches ibswitch_list]}
    [-fromnode node_name]
    [-unkey]
    [-smtpfrom "address"]
    [-smtpo "addresses"]
    [-precheckonly]
    [-modifyatprereq]
    [-resetforce]
    [-force]
    [-patchmgrloc patch_mgr_loc]
```

Parameters

Table A-69 rhpctl update workingcopy Command Parameters

Parameter	Description
-image <i>image_name</i>	Specify the name of a configured image from which to update a working copy
-root	Optionally, you can specify to use root credentials to access the remote node.

Glossary

action script

A script that defines the start, stop and check actions for a resource. The start action is invoked while starting the resource, the stop action for stopping the resource, and the check action while checking the running status of a resource.

administrator managed

Database administrators define on which servers a database resource should run, and place resources manually as needed. This is the management strategy used in previous releases.

agent

A program that contains the agent framework and user code to manage resources.

agent framework

A C library that enables users to plug in application-specific code to manage customized applications.

availability directive

Instructions to Oracle Clusterware to reconfigure the system when a server leaves or joins a cluster.

cardinality

The number of servers on which a [resource](#) can run, simultaneously.

client cluster

In a multicluster environment, a client cluster advertises its names with the [server cluster](#).

cluster

Multiple interconnected computers or servers that appear as if they are one server to end users and applications.

cluster-aware

Any application designed to be deployed using clusterware.

cluster administrator

An administrator who can manage a certain part of a cluster based on set policies and privileges.

cluster configuration policy

A document for policy-managed clusters, which contains exactly one definition for each server pool defined in the system.

cluster configuration policy set

A document that defines the names of all server pools configured in the cluster, which contains one or more configuration policies. Only one policy can be in effect at any one time, but administrators can set different policies to be in effect at different dates or times of the day in accordance with business needs and system demands.

Cluster Health Monitor

Detects and analyzes operating system and cluster resource-related degradation and failures.

cluster resource

A resource that is aware of the cluster environment and subject to cross-node switchover and failover.

Cluster Time Synchronization Service

A time synchronization mechanism that ensures that all internal clocks of all nodes in a cluster are synchronized.

Cluster Verification Utility (CVU)

A tool that verifies a wide range of Oracle RAC components such as shared storage devices, networking configurations, system requirements, Oracle Clusterware, groups, and users.

database cloud

A set of databases integrated by the global service and load management framework into a single virtual server that offers one or more global services, while ensuring high performance, availability, and optimal utilization of resources.

dependency

The relationship between two or more resources. and the interaction expressed between them.

disk group

An Oracle ASM disk group is a collection of disks that Oracle ASM manages as a unit. Within a disk group, Oracle ASM exposes a file system interface for Oracle Database files. The content of files that is stored in a disk group is evenly distributed, or striped, to eliminate hot spots and to provide uniform performance across the disks. Oracle ASM files may also be optionally mirrored within a disk group. The performance of disks in a disk group is comparable to the performance of raw devices.

Dynamic Host Configuration Protocol (DHCP)

A network application protocol used by devices (DHCP clients) to obtain configuration information for operation in an Internet Protocol network. This protocol reduces system administration workload, allowing devices to be added to the network with little or no manual intervention.

fixup script

Oracle Universal Installer detects when minimum requirements for installation are not completed, and creates shell script programs, called fixup scripts, to resolve many incomplete system configuration requirements. If Oracle Universal Installer detects an incomplete task, it prompts you to create a fixup script and then to run the fixup script in a separate terminal session. You can also generate fixup scripts with certain CVU commands by using the `-fixup` flag.

gold image

A copy of a software only, installed Oracle home, where the home-specific details are unavailable. This enables you to easily copy an image of an Oracle home to a new host on a new file system to serve as an active usable Oracle home.

A gold image can correspond, generally, to any application but in the context of this document, gold images correspond to Oracle Databases. Also, a gold image is *not* a ship home, which means that you do not have to run Oracle Universal Installer when deploying a gold image.

Grid Home client

The Grid Home client is a remote [Oracle Grid Infrastructure](#) cluster that subscribes to the [Fleet Patching and Provisioning Server](#) for provisioning of [gold images](#).

Oracle Grid Infrastructure

The software that provides the infrastructure for an enterprise grid architecture. In a cluster this software includes Oracle Clusterware and Oracle ASM. For a standalone server, this software includes Oracle Restart and Oracle ASM. Oracle Database 12c combines these infrastructure products into one software installation called the *Oracle Grid Infrastructure home* (`Grid_home`).

Grid Naming Service (GNS)

A generic service which resolves the names of hosts in a delegated normal DNS zone by mapping them to IP addresses within the zone. GNS enables the use of Dynamic Host Configuration Protocol (DHCP) address for Oracle RAC database nodes, simplifying deployment. GNS also resolves host names passed back from a SCAN listener.

Hub anchor

A Hub Node in an Oracle Flex Cluster that acts as the connection point for purposes of cluster membership for one or more other supported nodes. Those nodes exchange heartbeats with a single Hub anchor.

Hub Node

A node in an [Oracle Flex Cluster](#) that is tightly connected with other servers and has direct access to shared storage.

image

Master copy of Oracle database home software which resides on the Fleet Patching and Provisioning Server.

IPv4

Internet Protocol Version 4. IPv4 is the current standard for the IP protocol. IPv4 uses 32-bit (four-byte) addresses, which are typically represented in dotted-decimal notation. The decimal value of each octet is separated by a period, as in 192.168.2.22.

IPv6

Internet Protocol Version 6. The protocol designed to replace IPv4. In IPv6, an IP address is typically represented in eight fields of hexadecimal values separated by

colons, as in 2001:0DB8:0000:0000:0000:0000:1428:57AB. In some cases, fields with 0 values can be compressed, as in 2001:DB8::1428:57AB.

local resource

A resource that runs on the nodes of a cluster but is unaware of anything outside of the scope of the node.

OCR writer

Each CRSD process also acts as an OCR server. One of the CRSD processes in the cluster is the OCR server that performs I/O to the disk group or file, or block or raw device.

Oracle Automatic Storage Management (Oracle ASM)

Oracle ASM manages the storage disks used by Oracle Clusterware and Oracle RAC in disk groups. By default, Oracle Clusterware uses Oracle ASM to store OCR and voting files.

Oracle Cluster Registry (OCR)

The Oracle RAC configuration information repository that manages information about the cluster node list and instance-to-node mapping information. OCR also manages information about Oracle Clusterware resource profiles for customized applications.

Oracle Clusterware

Software that allows groups (clusters) of connected servers to operate or be controlled as a unit.

Oracle Clusterware stack

The Oracle Clusterware stack includes Oracle Cluster Ready Services, Event Manager, Cluster Synchronization Services, and Oracle ASM (if used).

Oracle Fleet Patching and Provisioning Server

The Oracle Fleet Patching and Provisioning Server is one server on the server cluster that can hold a repository of [gold images](#).

Oracle Flex Cluster

Large clusters that are made of up of [Hub Nodes](#) and other supported nodes, where the Hub Nodes form a cluster using current membership algorithms and the other nodes connect for membership to a single Hub Node.

policy managed

Database administrators specify the server pool (excluding Generic or Free) in which the database resource runs. Oracle Clusterware places the database resource on a server.

reader node

A reader node is a nodes on which an Oracle RAC database instance runs.

resource

A database, application, or process managed by Oracle Clusterware.

resource group

A container for an application that is comprised of various logically related resources that Oracle Clusterware manages and monitors as a single entity.

resource state

The state of a particular resource at any given time that determines its availability to the cluster.

resource type

Defines whether a resource is either a [cluster resource](#) or a [local resource](#).

server categorization

A method of identifying servers in the cluster into different categories by using a set of server attributes. Administrators can configure server pools to restrict which categories they accept. Server categories are created by providing attributes for the `SERVER_CATEGORY` parameter.

server cluster

In a multicluster environment, a server cluster is a cluster in which the Grid Naming Service (GNS) process runs.

server pool

A logical division of servers in a cluster into a group that hosts applications, databases, or both.

Single Client Access Name (SCAN)

A single name that resolves to three IP addresses in the public network.

start effort evaluation

The process that Oracle Clusterware goes through when it starts a resource. During this process, Oracle Clusterware considers resource dependencies contained in the profile of the resource.

state

A set of values that describes what the condition of a particular resource.

working copy

An Oracle ACFS snapshot of a [gold image](#) that can either be a software-only installed Oracle home or an instantiated, configured Oracle home.

zone data

The GNS daemon records saved in the Oracle Cluster Registry.

Index

C

cluster
adding a node, [4-8](#)

D

database home
provisioning a working copy of, [2-19](#)

F

Fleet Patching and Provisioning, [A-1](#)
about, [1-1](#)
architecture, [1-8](#)
components
 Fleet Patching and Provisioning Client, [1-11](#)
 Fleet Patching and Provisioning Server, [1-10](#)
 Fleet Patching and Provisioning targets, [1-11](#)
creating databases on a working copy, [2-19](#)
deploying Oracle Grid Infrastructure, [2-5](#)
features, [1-1](#)
gold image, [1-1](#)
gold image distribution, [1-16](#)
image series, [1-21](#)
image state, [1-21](#)
image type, [1-22](#)
images, [1-16](#)
job scheduler, [2-40](#)
managing Clients, [3-1](#)
moving databases between working copies, [2-20](#)
notifications, [1-19](#)
Oracle Database software management, [2-18](#)
patching Oracle Grid Infrastructure (non-rolling), [2-9](#)
patching Oracle Grid Infrastructure (rolling), [2-8](#)
persistent home path, [2-33](#)
provisioned software
 storage options, [1-26](#)

Fleet Patching and Provisioning (*continued*)
 provisioning a working copy of a database home, [2-19](#)
 provisioning for a different user, [1-27](#)
 roles, [1-13](#)
 basic built-in, [1-13](#)
 composite built-in, [1-13](#)
 upgrading Oracle Database software, [2-23](#)
 user actions
 creating web server, [4-10](#)
 user groups management, [1-23](#)
 user-defined actions, [2-34](#)
Fleet Patching and Provisioning Client
 assigning roles to users, [3-5](#)
 creating, [3-1](#)
 creating users, [3-5](#)
 enabling and disabling, [3-3](#)
 managing, [3-1](#)
 managing the password, [3-5](#)
Fleet Patching and Provisioning commands
 See RHPCTL
Fleet Patching and Provisioning Server, [1-1](#)
 creating, [1-19](#)
 Oracle Grid Infrastructure software management, [2-5](#)
 propagating images between, [1-27](#)

G

gold image
 Fleet Patching and Provisioning, [1-1](#)
gold images
 adding, [4-9](#)
 adding to Fleet Patching and Provisioning server, [1-20](#)

I

independent automaton, [2-13](#), [2-22](#)

J

job scheduler
 Fleet Patching and Provisioning, [2-40](#)

O

- Oracle Database
 - creating on a working copy, [2-19](#)
 - moving between working copies, [2-20](#)
 - patching, [2-22](#), [4-5](#), [4-6](#)
 - scaling, [4-8](#)
 - upgrading, [4-7](#)
- Oracle Exadata database node
 - combined with Oracle Grid Infrastructure
 - patching, [2-24](#)
- Oracle FPP, [1-1](#)
- Oracle Grid Infrastructure
 - combined with Oracle Exadata database
 - node patching, [2-24](#)
 - creating, [4-1](#)
 - in batches, [2-1](#)
 - patching, [2-13](#), [4-4](#), [4-5](#)
 - patching using Fleet Patching and Provisioning, [2-1](#), [2-8](#)
 - patching using the non-rolling method, [2-9](#)
 - patching using the rolling method, [2-8](#)
 - provisioning, [2-6](#)
 - upgrading, [4-3](#)
 - upgrading using Fleet Patching and Provisioning, [2-15](#)
 - zero-downtime patching, [2-12](#)
- Oracle Restart
 - patching, upgrading, [2-42](#)

P

- patching
 - automated recovery options, [2-14](#)
 - combined Oracle Grid Infrastructure and Oracle Database, [2-10](#)
 - error prevention, [2-14](#)
- patching software
 - Fleet Patching and Provisioning-defined, [2-1](#)
 - in batches, [2-1](#)
 - user-defined, [2-1](#)
- persistent home path, [2-33](#)
- pluggable database
 - provisioning, [4-3](#)
- provisioning software, [1-23](#)

R

- RHPCTL, [A-2](#)
 - authentication options, [1-12](#)
 - collect osconfig, [A-59](#)
 - command syntax, [A-1](#)
 - commands, [A-59–A-62](#), [A-71](#), [A-72](#)
 - add client, [A-4](#)
 - add credentials, [A-13](#)

RHPCTL (continued)

- commands (*continued*)
 - add database, [A-14](#)
 - add image, [A-44](#)
 - add imagetype, [A-53](#)
 - add role, [A-62](#)
 - add series, [A-66](#)
 - add useraction, [A-75](#)
 - add workingcopy, [A-79](#)
 - addnode database, [A-17](#)
 - addnode gihome, [A-35](#)
 - addnode workingcopy, [A-85](#)
 - addpdb database, [A-18](#)
 - allow client, [A-5](#)
 - allow image, [A-45](#)
 - allow imagetype, [A-54](#)
 - delete audit, [A-2](#)
 - delete client, [A-6](#)
 - delete credentials, [A-14](#)
 - delete database, [A-21](#)
 - delete image, [A-45](#)
 - delete imagetype, [A-54](#)
 - delete job, [A-57](#)
 - delete role, [A-64](#)
 - delete series, [A-67](#)
 - delete user, [A-73](#)
 - delete useraction, [A-76](#)
 - delete workingcopy, [A-86](#)
 - deleteimage series, [A-67](#)
 - deletenode database, [A-22](#)
 - deletenode gihome, [A-37](#)
 - deletepdb database, [A-20](#)
 - deploy image, [A-46](#)
 - disallow client, [A-7](#)
 - disallow image, [A-46](#)
 - disallow imagetype, [A-54](#)
 - discover client, [A-8](#)
 - export client, [A-9](#)
 - grant role, [A-64](#)
 - import image, [A-47](#)
 - insertimage series, [A-68](#)
 - instantiate image, [A-49](#)
 - modify audit, [A-2](#)
 - modify client, [A-9](#)
 - modify image, [A-50](#)
 - modify imagetype, [A-55](#)
 - modify user, [A-73](#)
 - modify useraction, [A-77](#)
 - move database, [A-24](#)
 - move gihome, [A-38](#)
 - movepdb database, [A-28](#)
 - promote image, [A-52](#)
 - query audit, [A-3](#)
 - query client, [A-10](#)
 - query image, [A-50](#)

RHPCTL (*continued*)

- commands (*continued*)
- query imagetype, [A-55](#)
- query job, [A-57](#)
- query role, [A-65](#)
- query series, [A-69](#)
- query server, [A-71](#)
- query useraction, [A-78](#)
- query workingcopy, [A-88](#)
- register user, [A-74](#)
- revoke role, [A-66](#)
- subscribe series, [A-70](#)
- uninstantiate image, [A-52](#)
- unsubscribe series, [A-71](#)
- update client, [A-12](#)
- update exadata, [A-34](#)
- update workingcopy, [A-89](#)
- upgrade database, [A-29](#)
- upgrade gihome, [A-42](#)
- verify client, [A-12](#)
- zdtupgrade database, [A-31](#)

compare osconfig, [A-59](#)
disable osconfig, [A-60](#)
enable osconfig, [A-60](#)

RHPCTL (*continued*)

- export server, [A-71](#)
- help, [A-2](#)
- query osconfig, [A-61](#)
- query peerserver, [A-62](#)
- register server, [A-72](#)
- unregister server, [A-72](#)

W

working copy

- creating on the Fleet Patching and Provisioning client, [1-23](#)
- creating on the Fleet Patching and Provisioning Server, [1-23](#)

Z

- zero-downtime database upgrade, [1-1](#)
- zero-downtime upgrade, [2-27](#)
 - customizing, [2-32](#)
 - running with Oracle Data Guard, [2-31](#)
 - running with Oracle GoldenGate, [2-29](#)