G05DRF - NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

G05DRF returns a pseudo-random integer variate from a Poisson distribution with mean λ .

2 Specification

INTEGER FUNCTION GO5DRF(ALAMDA, IFAIL)

 $\begin{array}{ll} {\tt INTEGER} & {\tt IFAIL} \\ {\tt \it real} & {\tt ALAMDA} \end{array}$

3 Description

The distribution of a Poisson random variable X is given by

$$P(X = x) = \frac{\lambda^x e^{-\lambda}}{x!}$$
 if $x = 0, 1, 2, ...$

$$P(X=x)=0$$
 otherwise.

The methods used by G05DRF have low set-up times and are designed for efficient use when the value of the parameter λ changes during the simulation. For large samples from a distribution with fixed λ using G05ECF to set up a reference vector for subsequent use by G05EYF may be more efficient.

When $\lambda < 7.5$ the product of uniforms method is used, see for example Dagpunar [2]. For larger values of λ an envelope rejection method is used with a target distribution:

$$f(x) = \frac{1}{3} \qquad \text{if } |x| \le 1$$

$$f(x) = \frac{1}{3}|x|^{-3}$$
 otherwise.

This distribution is generated using a ratio of uniforms method. A similar approach has also been suggested by Ahrens and Dieter [1]. The basic method is combined with quick acceptance and rejection tests given by MacLaren [3]. For values of $\lambda \geq 87$ Stirling's approximation is used in the computation of the Poisson distribution function, otherwise tables of factorials are used as suggested by MacLaren [3].

4 References

- [1] Ahrens J H and Dieter U (1989) A convenient sampling method with bounded computation times for Poisson distributions Amer. J. Math. Management Sci. 1–13
- [2] Dagpunar J (1988) Principles of Random Variate Generation Oxford University Press
- [3] Maclaren N M (1990) A Poisson random number generator Personal Communication

5 Parameters

1: ALAMDA - real

On entry: the parameter, λ , of the distribution.

Constraint: ALAMDA > 0.0 and $2 \times$ ALAMDA \leq MAXINT, where MAXINT is the largest integer representable on the machine (see X02BBF).

[NP3445/2/pdf] G05DRF.1

2: IFAIL — INTEGER Input/Output

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors detected by the routine:

```
IFAIL = 1
```

On entry, ALAMDA ≤ 0.0 .

IFAIL = 2

On entry, $2 \times ALAMDA > MAXINT$.

7 Accuracy

Not applicable.

8 Further Comments

The methods used by G05DRF have low set-up times and are designed for efficient use when the value of the parameter λ changes during the simulation. For large samples from a distribution with fixed λ using G05ECF to set up a reference vector for subsequent use by G05EYF may be more efficient.

9 Example

The example program prints five pseudo-random variates from Poisson distributions with parameters 1, 5, 15, 50 and 100 respectively, generated by G05DRF after initialisation by G05CBF.

The generator mechanism used is selected by an initial call to G05ZAF.

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
* GO5DRF Example Program Text
```

- * NAG Fortran SMP Library, Release 2. NAG Copyright 2000.
- * .. Parameters ..

INTEGER NIN, NOUT
PARAMETER (NIN=5,NOUT=6)

* .. Local Scalars ..

DOUBLE PRECISION A

INTEGER IFAIL, X

.. External Functions ..
INTEGER GO5DRF
EXTERNAL GO5DRF

* .. External Subroutines ..

EXTERNAL GOSCBF, GOSZAF

* .. Executable Statements .. CALL G05ZAF('0')

G05DRF.2 [NP3445/2/pdf]

```
WRITE (NOUT,*) 'GO5DRF Example Program Results'
      WRITE (NOUT,*)
      Skip heading in data file
      READ (NIN,*)
      IFAIL = 0
      CALL GO5CBF(0)
  20 CONTINUE
     READ (NIN, *, END=40, ERR=40) A
      IF (A.LE.O.ODO) GO TO 40
      X = GO5DRF(A,IFAIL)
      WRITE (NOUT, 99999) X
      GO TO 20
  40 CONTINUE
      STOP
99999 FORMAT (1X,I10)
      END
```

9.2 Program Data

```
GO5DRF Example Program Data
1.0
5.0
15.0
50.0
100.0
-1.0
```

9.3 Program Results

GO5DRF Example Program Results

[NP3445/2/pdf] G05DRF.3 (last)