NAG Fortran Library Routine Document

E04MHF/E04MHA

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

To supply individual optional parameters to E04MFF/E04MFA. More precisely, E04MHF must be used to supply optional parameters to E04MFF and E04MHA must be used to supply optional parameters to E04MFA.

E04MHA is a version of E04MHF that has additional parameters in order to make it safe for use in multithreaded applications (see Section 5 below). The initialisation routine E04WBF **must** have been called prior to calling E04MHA.

2 Specifications

2.1 Specification for E04MHF

SUBROUTINE E04MHF(STRING) CHARACTER*(*) STRING

2.2 Specification for E04MHA

SUBROUTINE E04MHA(STRING, LWSAV, IWSAV, RWSAV, INFORM)INTEGERIWSAV(610), INFORMrealRWSAV(475)LOGICALLWSAV(120)CHARACTER*(*)STRING

3 Description

E04MHF/E04MHA may be used to supply values for optional parameters to the corresponding routines E04MFF/E04MFA. It is only necessary to call E04MHF/E04MHA for those parameters whose values are to be different from their default values. One call to E04MHF/E04MHA sets one parameter value.

Each optional parameter is defined by a single character string, of up to 72 characters, consisting of one or more items. The items associated with a given option must be separated by spaces, or equals signs [=]. Alphabetic characters may be upper or lower case. The string

Print level = 1

is an example of a string used to set an optional parameter. For each option the string contains one or more of the following items:

- (a) A mandatory keyword.
- (b) A phrase that qualifies the keyword.
- (c) A number that specifies an INTEGER or *real* value. Such numbers may be up to 16 contiguous characters in Fortran's I, F, E or D formats, terminated by a space if this is not the last item on the line.

Blank strings and comments are ignored. A comment begins with an asterisk (*) and all subsequent characters in the string are regarded as part of the comment.

For E04MHF, each user-specified option is normally printed as it is defined, on the current advisory message unit (see X04ABF), but this printing may be suppressed using the keyword **nolist**. Thus the statement

CALL EO4MHF ('Nolist')

[NP3546/20A]

suppresses printing of this and subsequent options. Printing will automatically be turned on again after a call to E04MFF and may be turned on again at any time using the keyword **list**.

For E04MHA printing is turned off by default, but may be turned on at any time using the keyword list.

Optional parameter settings are preserved following a call to E04MFF/E04MFA and so the keyword **defaults** is provided to allow you to reset all the optional parameters to their default values prior to a subsequent call to E04MFF/E04MFA.

A complete list of optional parameters, their abbreviations, synonyms and default values is given in Section 11 of the document for E04MFF/E04MFA.

4 References

None.

5 Parameters

1: STRING – CHARACTER*(*)

On entry: a single valid option string (as described in Section 3 above and in Section 11 of the document for E04MFF/E04MFA).

Note: the following are additional parameters for specific use with E04MHA. Users of E04MHF therefore need not read the remainder of this section.

2:	LWSAV(120) – LOGICAL array	Workspace
3:	IWSAV(610) – INTEGER array	Workspace
4:	RWSAV(475) - real array	Workspace

The arrays LWSAV, IWSAV and RWSAV **must not** be altered between calls to any of the routines E04WBF, E04MFA, E04MGA or E04MHA.

5: INFORM – INTEGER

On exit: contains zero if a valid option string has been supplied and a value > 0 otherwise (see Section 6).

6 Error Indicators and Warnings

Errors or warnings detected by the routine:

INFORM = 5

The supplied option is invalid. Check that the keywords are neither ambiguous nor misspelt.

7 Accuracy

Not applicable.

8 Further Comments

 $\rm E04MGF/E04MGA$ may also be used to supply optional parameters to the corresponding routines $\rm E04MFF/E04MFA.$

9 Example

See Section 9 of the document for E04MGF/E04MGA.

Output

Input