

NAG Fortran Library Routine Document

F06PFF (DTRMV)

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

F06PFF (DTRMV) performs one of the matrix-vector operations

$$x \leftarrow Ax \quad \text{or} \quad x \leftarrow A^T x,$$

where A is an n by n real triangular matrix, and x is an n element real vector.

2 Specification

```
SUBROUTINE F06PFF (UPLO, TRANS, DIAG, N, A, LDA, X, INCX)
  INTEGER          N, LDA, INCX
  double precision A(LDA,*), X(*)
  CHARACTER*1     UPLO, TRANS, DIAG
```

The routine may be called by its BLAS name *dtrmv*.

3 Description

None.

4 References

None.

5 Parameters

- 1: UPLO – CHARACTER*1 *Input*
On entry: specifies whether A is upper or lower triangular as follows:
 if UPLO = 'U', A is upper triangular;
 if UPLO = 'L', A is lower triangular.
Constraint: UPLO = 'U' or 'L'.
- 2: TRANS – CHARACTER*1 *Input*
On entry: specifies the operation to be performed as follows:
 if TRANS = 'N', $x \leftarrow Ax$;
 if TRANS = 'T' or 'C', $x \leftarrow A^T x$.
Constraint: TRANS = 'N', 'T' or 'C'.
- 3: DIAG – CHARACTER*1 *Input*
On entry: specifies whether A has non-unit or unit diagonal elements, as follows:
 if DIAG = 'N', the diagonal elements are stored explicitly;
 if DIAG = 'U', the diagonal elements are assumed to be 1, and are not referenced.
Constraint: DIAG = 'N' or 'U'.

- 4: N – INTEGER *Input*
On entry: n , the order of the matrix A .
Constraint: $N \geq 0$.
- 5: A(LDA,*) – **double precision** array *Input*
Note: the second dimension of the array A must be at least $\max(1, N)$.
On entry: the n by n triangular matrix A . If UPLO = 'U', A is upper triangular and the elements of the array below the diagonal are not referenced; if UPLO = 'L', A is lower triangular and the elements of the array above the diagonal are not referenced. If DIAG = 'U', the diagonal elements of A are not referenced, but are assumed to be 1.
- 6: LDA – INTEGER *Input*
On entry: the first dimension of the array A as declared in the (sub)program from which F06PFF (DTRMV) is called.
Constraint: $LDA \geq \max(1, N)$.
- 7: X(*) – **double precision** array *Input/Output*
On entry: the vector x .
On exit: the updated vector x .
- 8: INCX – INTEGER *Input*
On entry: the increment in the subscripts of X between successive elements of x .
Constraint: $INCX \neq 0$.

6 Error Indicators and Warnings

None.
