Distributed Computing Toolbox

For Use with MATLAB®

Computation

Visualization

Programming



User's Guide

 $Version \ 2$

How to Contact The MathWorks:

	www.mathworks.com comp.soft-sys.matlab	Web Newsgroup
@	support@mathworks.com suggest@mathworks.com bugs@mathworks.com doc@mathworks.com service@mathworks.com info@mathworks.com	Technical support Product enhancement suggestions Bug reports Documentation error reports Order status, license renewals, passcodes Sales, pricing, and general information
7	508-647-7000	Phone
	508-647-7001	Fax
	The MathWorks, Inc. 3 Apple Hill Drive Natick, MA 01760-2098	Mail

For contact information about worldwide offices, see the MathWorks Web site.

Distributed Computing Toolbox User's Guide © COPYRIGHT 2004-2005 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. It this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB, Simulink, Stateflow, Handle Graphics, Real-Time Workshop, and xPC TargetBox are registered trademarks of The MathWorks, Inc.

Other product or brand names are trademarks or registered trademarks of their respective holders.

Patents

The MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

Revision History

November 2004	Online only
March 2005	Online only
Septermber 2005	Online only
November 2005	Online only

New for Version 1.0 (Release 14SP1+) Revised for Version 1.0.1 (Release 14SP2) Revised for Version 1.0.2 (Release 14SP3) Revised for Version 2.0 (Release 14SP3+)



Getting Started

What Are the Distributed Computing Products?	1-2
Determining Product Installation and Versions	1-3
Toolbox and Engine Components	1-4
Job Managers, Workers, and Clients	1-4
Third-Party Schedulers	1-5
Components on Mixed Platforms or Heterogeneous Clusters .	1-7
The MATLAB Distributed Computing Engine Service	1-7
Components Represented in the Client	1-7
Using the Distributed Computing Toolbox	
Overview	1-8
Overview Example: Programming a Basic Job with a Job Manager	1-8 1-8
Overview	1-8 1-8 1-9
Overview Example: Programming a Basic Job with a Job Manager Example: Evaluating a Basic Function Example: Programming a Basic Job with an LSF Scheduler	1-8 1-8 1-9 1-10
Overview Example: Programming a Basic Job with a Job Manager Example: Evaluating a Basic Function	1-8 1-8 1-9 1-10

1

Programming Distributed and Parallel Applications **2**

Program Development Guidelines	2-2
Life Cycle of a Job	2-3
Evaluating Functions in a Cluster	2-5
Evaluating Functions Synchronously Evaluating Functions Asynchronously	

Programming Distributed Jobs	. 2-9
Using a Job Manager	. 2-9
Using an LSF Scheduler	
Using a Generic Scheduler	2-27
Programming Parallel Jobs	2-37
Using a Job Manager	2-38
Using an mpiexec Scheduler	2-40
Further Notes on Parallel Jobs	2-43
Programming with User Configurations	
Defining Configurations	
Applying Configurations in Client Code	2-45
Programming Tips and Notes	2-47
Saving or Sending Objects	2-47
Current Working Directory of MATLAB Worker	2-47
Using clear functions	
Running Tasks That Call Simulink	2-48
Using the pause Function	2-48
Transmitting Large Amounts of Data	2-48
Interrupting a Job	2-48
IPv6 on Macintosh	2-48
Speeding Up a Job	2-49
Troubleshooting and Debugging	2-50
Object Data Size Limitations	2-50
File Access and Permissions	
No Results from Job	2-53
Connection Problems Between Client and Job Manager	2-54

	Г
–	
J	l

Functions — Categorical List	3-2
General Functions	3-2
Job Manager Functions	3-3
Scheduler Functions	3-3
Job Functions	3-3
Parallel Job Functions	3-4
Task Functions	3-4
Worker Functions	3-4
Functions — Alphabetical List	3-6

Property Reference

4 [

Properties – Categorical List	4-2
Job Manager Properties	4-2
Scheduler Properties	4-3
Job Properties	4-3
Task Properties	4-5
Worker Properties	4-6
Properties — Alphabetical List	4-7

Glossary

Index

Getting Started

This chapter provides information you need to get started with the Distributed Computing Toolbox and the MATLAB[®] Distributed Computing Engine. The sections are as follows.

What Are the Distributed Computing Products? (p. 1-2)	Overview of the Distributed Computing Toolbox and the MATLAB Distributed Computing Engine, and their capabilities
Toolbox and Engine Components (p. 1-4)	Descriptions of the parts and configurations of a distributed computing setup
Using the Distributed Computing Toolbox (p. 1-8)	Introduction to Distributed Computing Toolbox programming with a basic example
Getting Help (p. 1-12)	Explanation of how to get help on toolbox functions

What Are the Distributed Computing Products?


The Distributed Computing Toolbox and the MATLAB Distributed Computing Engine enable you to coordinate and execute independent MATLAB operations simultaneously on a cluster of computers, speeding up execution of large MATLAB jobs.

A *job* is some large operation that you need to perform in your MATLAB session. A job is broken down into segments called *tasks*. You decide how best to divide your job into tasks. You could divide your job into identical tasks, but tasks do not have to be identical.

The MATLAB session in which the job and its tasks are defined is called the *client* session. Often, this is on the machine where you program MATLAB. The client uses the Distributed Computing Toolbox to perform the definition of jobs and tasks. The MATLAB Distributed Computing Engine is the product that performs the execution of your job by evaluating each of its tasks and returning the result to your client session.

The *job manager* is the part of the engine that coordinates the execution of jobs and the evaluation of their tasks. The job manager distributes the tasks for evaluation to the engine's individual MATLAB sessions called *workers*. Use of the MathWorks job manager is optional; the distribution of tasks to workers can also be performed by a third-party scheduler, such as LSF.

See the "Glossary" for definitions of the distributed computing terms used in this manual.



Basic Distributed Computing Configuration

Determining Product Installation and Versions

To determine if the Distributed Computing Toolbox is installed on your system, type this command at the MATLAB prompt.

ver

When you enter this command, MATLAB displays information about the version of MATLAB you are running, including a list of all toolboxes installed on your system and their version numbers.

You can run the ver command as part of a task in a distributed application to determine what version of the MATLAB Distributed Computing Engine is installed on a worker machine. Note that the toolbox and engine must be the same version.

Toolbox and Engine Components


Job Managers, Workers, and Clients

The job manager can be run on any machine on the network. The job manager runs jobs in the order in which they are submitted, unless any jobs in its queue are promoted, demoted, canceled, or destroyed.

Each worker is given a task from the running job by the job manager, executes the task, returns the result to the job manager, and then is given another task. When all tasks for a running job have been assigned to workers, the job manager starts running the next job with the next available worker.


A MATLAB Distributed Computing Engine setup usually includes many workers that can all execute tasks simultaneously, speeding up execution of large MATLAB jobs. It is generally not important which worker executes a specific task. The workers evaluate tasks one at a time, returning the results to the job manager. The job manager then returns the results of all the tasks in the job to the client session.

Note For testing your application locally or other purposes, you can configure a single computer as client, worker, and job manager. You can also have more than one worker session or more than one job manager session on a machine.



Interactions of Distributed Computing Sessions

A large network might include several job managers as well as several client sessions. Any client session can create, run, and access jobs on any job manager, but a worker session is registered with and dedicated to only one job manager at a time. The following figure shows a configuration with multiple job managers.



Configuration with Multiple Clients and Job Managers

Third-Party Schedulers

As an alternative to using the MathWorks job manager, you can use a third-party scheduler. This could be a Platform Computing LSF scheduler, an mpiexec scheduler, or a generic scheduler.

Choosing between a Scheduler and Job Manager

You should consider the following when deciding to use a scheduler or the MathWorks job manager for distributing your tasks:

• Does your cluster already have a scheduler?

If you already have a scheduler, you may be required to use it as a means of controlling access to the cluster. Your existing scheduler might be just as easy to use as a job manager, so there might be no need for the extra administration involved.

• Is the handling of distributed computing jobs the only cluster scheduling management you need?

The MathWorks job manager is designed specifically for MathWorks distributed computing applications. If other scheduling tasks are not needed, a third-party scheduler might not offer any advantages.

• Is there a file sharing configuration on your cluster already?

The MathWorks job manager can handle all file and data sharing necessary for your distributed computing applications. This might be helpful in configurations where shared access is limited.

• Are you interested in batch mode or managed interactive processing?

When you use a job manager, worker processes usually remain running at all times, dedicated to their job manager. With a third-party scheduler, workers are run as applications that are started for the evaluation of tasks, and stopped when their tasks are complete. If tasks are small or take little time, starting a worker for each one might involve too much overhead time.

• Are there security concerns?

Your own scheduler may be configured to accommodate your particular security requirements.

• How many nodes are on your cluster?

If you have a large cluster, you probably already have a scheduler. Consult your MathWorks representative if you have questions about cluster size and the job manager.

• Who administers your cluster?

The person administering your cluster might have a preference for how jobs are scheduled.

• Do you need to monitor your job's progress or access intermediate data?

A job run by the job manager supports events and callbacks, so that particular functions can run as each job and task progresses from one state to another.

Components on Mixed Platforms or Heterogeneous Clusters

The Distributed Computing Toolbox and MATLAB Distributed Computing Engine are supported on Windows, UNIX, and Macintosh platforms. Mixed platforms are supported, so that the clients, job managers, and workers do not have to be on the same platform. The cluster can also be comprised of both 32-bit and 64-bit machines, so long as your data does not exceed the limitations posed by the 32-bit systems.

In a mixed-platform environment, system administrators should be sure to follow the proper installation instructions for the local machine on which you are installing the software.

The MATLAB Distributed Computing Engine Service

If you are using the MathWorks job manager, every machine that hosts a worker or job manager session must also run the MATLAB Distributed Computing Engine (mdce) service.

The mdce service controls the worker and job manager sessions and recovers them when their host machines crash. If a worker or job manager machine crashes, when the mdce service starts up again (usually configured to start at machine boot time), it automatically restarts the job manager and worker sessions to resume their sessions from before the system crash. These processes are covered more fully in the MATLAB Distributed Computing Engine System Administrator's Guide.

Components Represented in the Client

A client session communicates with the job manager by calling methods and configuring properties of a *job manager object*. Though not often necessary, the client session can also access information about a worker session through a *worker object*.

When you create a job in the client session, the job actually exists in the job manager or in the scheduler's data location. The client session has access to the job through a *job object*. Likewise, tasks that you define for a job in the client session exist in the job manager or in the scheduler's data location, and you access them through *task objects*.

Using the Distributed Computing Toolbox

Overview

A typical Distributed Computing Toolbox client session includes the following steps. Details of each step appear in "Creating and Running Jobs" on page 2-9. A basic example follows in the next section.

- 1 Find a Job Manager (or scheduler) Your network may have one or more job managers available (but usually only one scheduler). The function you use to find a job manager or scheduler creates an object in your current MATLAB session to represent the job manager or scheduler that will run your job.
- 2 Create a Job You create a job to hold a collection of tasks. The job exists on the job manager (or scheduler's data location), but a job object in the local MATLAB session represents that job.
- **3** Create Tasks You create tasks to add to the job. Each task of a job can be represented by a task object in your local MATLAB session.
- **4** Submit a Job to the Job Queue for Execution When your job has all its tasks defined, you submit it to the queue in the job manager or scheduler. The job manager or scheduler distributes your job's tasks to the worker sessions for evaluation. When all of the workers are completed with the job's tasks, the job moves to the finished state.
- 5 Retrieve the Job's Results The resulting data from the evaluation of the job is available as a property value of each task object.
- **6** Destroy the Job When a job is complete and you have its results, you might want to permanently remove the job from the job manager. Once a job is destroyed, its data is gone forever.

Example: Programming a Basic Job with a Job Manager

This example illustrates the basic steps in creating and running a job that contains a few simple tasks. Each task performs a sum on an input array.

1 Find a job manager. Use findResource to locate a job manager and create the job manager object jm, which represents the job manager in the cluster whose name is MyJobManager running on the host JobMgrHost.

```
jm = findResource('scheduler','type','jobmanager', ...
'name','MyJobManager','LookupURL','JobMgrHost');
```

2 Create a job. Create job j on the job manager.

```
j = createJob(jm);
```

3 Create tasks. Create three tasks on the job j. Each task evaluates the sum of the array that is passed as an input argument.

createTask(j, @sum, 1, {[1 1]}); createTask(j, @sum, 1, {[2 2]}); createTask(j, @sum, 1, {[3 3]});

4 Submit the job to the queue. The job manager moves the job into the queue to be executed when workers are available.

submit(j);

5 Retrieve results. Wait for the job to complete, then get the results from all the job's tasks.

```
waitForState(j)
results = getAllOutputArguments(j)
results =
   [2]
   [4]
   [6]
```

6 Destroy the job. When you have the results, you can permanently remove the job from the job manager.

```
destroy(j)
```

Example: Evaluating a Basic Function

The dfeval function allows you to evaluate a function in a cluster of workers without having to define jobs and tasks yourself. When you can divide your job into similar tasks, using dfeval might be an appropriate way to run your job. Your cluster must use a MathWorks job manager for dfeval to work.

```
results = dfeval(@sum, {[1 1] [2 2] [3 3]})
results =
    [2]
    [4]
    [6]
```

This example runs the job as three tasks in the same way the previous example does.

For more information about dfeval and in what circumstances you can use it, see "Evaluating Functions in a Cluster" on page 2-5.

Example: Programming a Basic Job with an LSF Scheduler

This example illustrates the basic steps in creating and running a job by using a third-party scheduler instead of a MathWorks job manager. Each task performs a sum on an input array.

1 Find a scheduler. Use findResource to locate a scheduler and create the scheduler object sched, which represents your cluster's LSF scheduler.

```
sched = findResource('scheduler','type','LSF');
```

2 Create a job. Create job j on the scheduler.

```
j = createJob(sched);
```

3 Create tasks. Create three tasks on the job j. Each task evaluates the sum of the array that is passed as an input argument.

```
createTask(j, @sum, 1, {[1 1]});
createTask(j, @sum, 1, {[2 2]});
createTask(j, @sum, 1, {[3 3]});
```

4 Submit the job to the queue. The scheduler moves the job into the queue to be executed when nodes are available.

submit(j);

5 Retrieve results. Wait for the job to complete, then get the results from all the job's tasks.

```
waitForState(j)
```

```
results = getAllOutputArguments(j)
results =
   [2]
   [4]
   [6]
```

6 Destroy the job. When you have the results, you can permanently remove the job from the scheduler's data location.

destroy(j)

1

Getting Help

Command-Line Help

You can get command-line help on the object functions in the Distributed Computing Toolbox by using the syntax

```
help distcomp.objectType/functionName
```

For example, to get command-line help on the createTask function, type

help distcomp.job/createTask

The available choices for *objectType* are jobmanager, job, and task.

Listing Available Functions

To find the functions available for each type of object, type

methods(obj)

where obj is an object of one of the available types.

For example, to see the functions available for job manager objects, type

```
jm = findResource('jobmanager');
methods(jm)
```

To see the functions available for job objects, type

```
job1 = createJob(jm)
methods(job1)
```

To see the functions available for task objects, type

```
task1 = createTask(job1,1,@rand,{3})
methods(task1)
```

Help Browser

You can open the Help browser with the doc command. To open the browser on a specific reference page for a function or property, type

doc distcomp/RefName

where *RefName* is the name of the function or property whose reference page you want to read.

For example, to open the Help browser on the reference page for the $\verb|createJob|$ function, type

```
doc distcomp/createjob
```

To open the Help browser on the reference page for the UserData property, type

doc distcomp/userdata

Note The property or function name must be entered with lowercase letters, even though function names are case sensitive in other situations.

2

Programming Distributed and Parallel Applications

This chapter provides information you need for programming with the Distributed Computing Toolbox to define and run jobs. The sections are as follows.

Program Development Guidelines (p. 2-2)	Suggested method for program development
Life Cycle of a Job (p. 2-3)	Stages of a job from creation to completion
Evaluating Functions in a Cluster (p. 2-5)	How to run a job without having to program scheduler, job, and task objects
Programming Distributed Jobs (p. 2-9)	How to create a distributed job and run it on the MATLAB Distributed Computing Engine with a job manager or a third-party scheduler
Programming Parallel Jobs (p. 2-37)	How to create a parallel job and run it on the MATLAB Distributed Computing Engine with a job manager or an mpiexec scheduler
Programming with User Configurations (p. 2-44)	How to employ configurations for parameters and properties in your program
Programming Tips and Notes (p. 2-47)	Provides helpful hints for good programming practice
Troubleshooting and Debugging (p. 2-50)	Describes common programming errors and how to avoid them

Program Development Guidelines

When writing code for the Distributed Computing Toolbox, you should advance one step at a time in the complexity of your application. Verifying your program at each step prevents your having to debug several potential problems simultaneously. If you run into any problems at any step along the way, back up to the previous step and reverify your code.

The recommended programming practice for distributed computing applications is


- **1 Run code normally on your local machine.** First verify your functions so that as you progress, you are not trying to debug the functions and the distribution at the same time. Run your functions in a single instance of MATLAB on your local computer.
- **2** Run code distributed to only one node, where that node is likely the local computer running a MATLAB worker in addition to your MATLAB client. Create a job and task to verify that the function is working in a distributed computing model.
- **3** Distribute the code to two nodes. Expand your job to include two tasks, preferably executed on two different workers on different computers.
- **4 Distribute the code to N nodes.** Scale up your job to include as many tasks as you need.

Note The client session of MATLAB must be running the Java Virtual Machine (JVM) to use the Distributed Computing Toolbox. Do not start MATLAB with the -nojvm flag.

Life Cycle of a Job

When you create and run a job, it progresses through a number of stages. Each stage of a job is reflected in the value of the job object's State property, which can be pending, queued, running, or finished. Each of these stages is briefly described in this section.

The figure below illustrated the stages in the life cycle of a job. In the job manager, the jobs are shown categorized by their state. Some of the functions you use for managing a job are createJob, submit, and getAllOutputArguments.



Stages of a Job

The following table describes each stage in the life cycle of a job.

Job Stage	Description
Pending	You create a job on the scheduler with the createJob function in your client session of the Distributed Computing Toolbox. The job's first state is pending. This is when you define the job by adding tasks to it.
Queued	When you execute the submit function on a job, the scheduler places the job in the queue, and the job's state is queued. The scheduler executes jobs in the queue in the sequence in which they are submitted, all jobs moving up the queue as the jobs before them are finished. You can change the order of the jobs in the queue with the promote and demote functions.
Running	When a job reaches the top of the queue, the scheduler distributes the job's tasks to worker sessions for evaluation. The job's state is running. If more workers are available than necessary for a job's tasks, the scheduler begins executing the next job. In this way, there can be more than one job running at a time.
Finished	When all of a job's tasks have been evaluated, a job is moved to the finished state. At this time, you can retrieve the results from all the tasks in the job with the function getAllOutputArguments.

Note that when a job is finished, it remains in the job manager or DataLocation directory, even if you clear all the objects from the client session. The job manager or scheduler keeps all the jobs it has executed, until you restart the job manager in a clean state. Therefore, you can retrieve information from a job at a later time or in another client session, so long as the job manager has not been restarted with the -clean option.

To permanently remove completed jobs from the job manager or scheduler's data location, use the destroy function.

Evaluating Functions in a Cluster

In many cases, the tasks of a job are all the same, or there are a limited number of different kinds of tasks in a job. The Distributed Computing Toolbox offers a solution for these cases that alleviates you from having to define individual tasks and jobs when evaluating a function in a cluster of workers. The two ways of evaluating a function on a cluster are described in the following sections:

- "Evaluating Functions Synchronously" on page 2-5
- "Evaluating Functions Asynchronously" on page 2-7

Evaluating Functions Synchronously

When you evaluate a function in a cluster of computers with dfeval, you provide basic required information, such as the function to be evaluated, the number of tasks to divide the job into, and the variable into which the results are returned. *Synchronous* evaluation in a cluster means that MATLAB is blocked until the evaluation is complete and the results are assigned to the designated variable. So you provide the necessary information, while the Distributed Computing Toolbox handles all the job-related aspects of the function evaluation.

When executing the dfeval function, the toolbox performs all these steps of running a job:

- 1 Finds a job manager
- 2 Creates a job
- 3 Creates tasks in that job
- 4 Submits the job to the queue in the job manager
- **5** Retrieves the results from the job
- **6** Destroys the job

Scope of dfeval

By allowing the system to perform all the steps for creating and running jobs with a single function call, you do not have access to the full flexibility offered by the Distributed Computing Toolbox. However, this narrow functionality meets the requirements of many straightforward applications. To focus the scope of dfeval, the following limitations apply:

- You can pass property values to the job object, but you cannot set any task-specific properties, including callback functions
- All the tasks in the job must have the same number of input arguments.
- All the tasks in the job must have the same number of output arguments.
- If you are using a third-party scheduler instead of the job manager, you must use configurations in your call to dfeval. See "Programming with User Configurations" on page 2-44, and the reference page for dfeval.
- You do not have direct access to the job manager, job, or task objects, i.e., there are no objects in your MATLAB workspace to manipulate (though you can get them using findResource and the properties of the job manager). Note that dfevalasync returns a job object.
- Without access to the objects and their properties, you do not have control over the handling of errors.

Example: Using dfeval

Suppose the function myfun accepts three input arguments, and generates two output arguments. To run a job with four tasks that call myfun, you could type

```
[A, B] = dfeval(@myfun, {a b c d}, {e f g h}, {w x y z});
```

The number of elements of the input argument cell arrays determines the number of tasks in the job. All input cell arrays must have the same number of elements. In this example, there are four tasks.

Because myfun returns two arguments, the results of your job will be assigned to two cell arrays, A and B. These cell arrays will have four elements each, for the four tasks. The first element of A will have the first output argument from the first task, the first element of B will have the second argument from the first task, and so on.

Task Function Call	Results
myfun(a,e,w)	A{1}, B{1}
<pre>myfun(b,f,x)</pre>	A{2}, B{2}
myfun(c,g,y)	A{3}, B{3}
<pre>myfun(d,h,z)</pre>	A{4}, B{4}

The following table shows how the job is divided into tasks and where the results are returned.

So using one dfeval line would be equivalent to the following code, except that dfeval can run all the statements simultaneously on separate machines.

[A{1}, B{1}] = myfun(a,e,w); [A{2}, B{2}] = myfun(b,f,x); [A{3}, B{3}] = myfun(c,g,y); [A{4}, B{4}] = myfun(d,h,z);

For further details and examples of the dfeval function, see the dfeval reference page.

Evaluating Functions Asynchronously

The dfeval function operates synchronously, that is, it blocks the MATLAB command line until its execution is complete. If you want to send a job off to the job manager and get access to the command line while the job is being run *asynchronously*, you can use the dfevalasync function.

The dfevalasync function operates in the same way as dfeval, except that it does not block the MATLAB command line, and it does not directly return results.

To asynchronously run the example of the previous section, type

```
Job1 = dfevalasync(@myfun, 2, {a b c d}, {e f g h}, {w x y z});
```

Note that you have to specify the number of output arguments that each task will return (2, in this example).

The MATLAB session does not wait for the job to execute, but returns the prompt immediately. Instead of assigning results to cell array variables, the function creates a job object in the MATLAB workspace that you can use to access job status and results.

You can use the MATLAB session to perform other operations while the job is being run on the cluster. When you want to get the job's results, you should make sure it is finished before retrieving the data.

```
waitForState(Job1, 'finished')
data = getAllOutputArguments(Job1)
```

The structure of the output arguments is now slightly different than it was for dfeval. The getAllOutputArguments function returns all output arguments from all tasks in a single cell array, with one row per task. In this example, each row of the cell array data will have two elements. So, data{1,1} contains the first output argument from the first task, data{1,2} contains the second argument from the first task, and so on.

For further details and examples of the dfevalasync function, see the dfevalasync reference page.

Programming Distributed Jobs

A distributed job is one whose tasks do not directly communicate with each other. The tasks do not need to run simultaneously, and a worker might run several tasks of the same job in succession. Typically, all tasks perform the same or similar functions on different data sets in an *embarrassingly parallel* configuration.

The following sections describe how to program distributed jobs:

- "Using a Job Manager" on page 2-9
- "Using an LSF Scheduler" on page 2-19
- "Using a Generic Scheduler" on page 2-27

Using a Job Manager

Creating and Running Jobs

For jobs that are more complex or require more control than the functionality offered by dfeval, you have to program all the steps for creating and running of the job.

This section details the steps of a typical programming session with the Distributed Computing Toolbox using a MathWorks job manager:

- "Find a Job Manager" on page 2-10
- "Create a Job" on page 2-11
- "Create Tasks" on page 2-12
- "Submit a Job to the Job Queue" on page 2-12
- "Retrieve the Job's Results" on page 2-13

Note that the objects that the client session uses to interact with the job manager are only references to data that is actually contained in the job manager process, not in the client session. After jobs and tasks are created, you can shut down your client session and restart it, and your job is still stored in the job manager. You can find existing jobs using the findJob function or the Jobs property of the job manager object.

Find a Job Manager. You use the findResource function to identify available job managers and to create an object representing a job manager in your local MATLAB session.

To find a specific job manager, use parameter-value pairs for matching. In this example, MyJobManager is the name of the job manager, while MyJMhost is the hostname of the machine running the job manager lookup service.

If your network supports multicast, you can omit property values to search on, and findResource returns all available job managers.

```
all_managers = findResource('scheduler','type','jobmanager')
```

You can then examine the properties of each job manager to identify which one you want to use.

```
for i = 1:length(all_managers)
  get(all_managers(i))
end
```

When you have identified the job manager you want to use, you can isolate it and create a single object.

```
jm = all_managers(3)
```

Create a Job. You create a job with the createJob function. Although you execute this command in the client session, the job is actually created on the job manager.

```
job1 = createJob(jm)
```

This statement creates a job on the job manager jm, and creates the job object job1 in the client session. Use get to see the properties of this job object.

```
get(job1)
                      Name: 'job 3'
                         ID: 3
                  UserName: 'eng864'
                       Tag: ''
                     State: 'pending'
             RestartWorker: 0
                   Timeout: Inf
    MaximumNumberOfWorkers: 2.1475e+009
    MinimumNumberOfWorkers: 1
                CreateTime: 'Thu Oct 21 19:38:08 EDT 2004'
                SubmitTime: ''
                 StartTime: ''
                FinishTime: ''
                     Tasks: [Ox1 double]
          FileDependencies: {0x1 cell}
          PathDependencies: {0x1 cell}
                   JobData: []
                    Parent: [1x1 distcomp.jobmanager]
                  UserData: []
                 QueuedFcn: []
                RunningFcn: []
               FinishedFcn: []
```

Note that the job's State property is pending. This means the job has not been queued for running yet, so you can now add tasks to it.

The job manager's Jobs property is now a 1-by-1 array of distcomp.job objects, indicating the existence of your job.

```
get(jm)
```

```
Name: 'MyJobManager'
Hostname: 'bonanza'
HostAddress: {'123.123.123.123'}
Jobs: [1x1 distcomp.job]
State: 'running'
Configuration: ''
NumberOfBusyWorkers: 0
BusyWorkers: [0x1 double]
NumberOfIdleWorkers: 2
IdleWorkers: [2x1 distcomp.worker]
```

You can transfer files to the worker by using the FileDependencies property of the job object. For details, see the FileDependencies reference page and "Sharing Code" on page 2-13.

Create Tasks. After you have created your job, and while it is still in the pending state, you can create tasks for the job. Tasks define the functions to be evaluated by the workers during the running of the job. Often, the tasks of a job are all identical. In this example, each task will generate a 3-by-3 matrix of random numbers.

```
createTask(job1, @rand, 1, {3,3});
```

The Tasks property of job1 is now a 5-by-1 matrix of task objects.

```
get(job1,'Tasks')
ans =
    distcomp.task: 5-by-1
```

Submit a Job to the Job Queue. To run your job and have its tasks evaluated, you submit the job to the job queue.

submit(job1)

The job manager distributes the tasks of job1 to its registered workers for evaluation.

Retrieve the Job's Results. The results of each task's evaluation are stored in that task object's OutputArguments property as a cell array. Use getAllOutputArguments to retrieve the results from all the tasks in the job.

results = getAllOutputArguments(job1);

Display the results from each task.

results{1:5}

0.9501	0.4860	0.4565
0.2311	0.8913	0.0185
0.6068	0.7621	0.8214
0.4447	0.9218	0.4057
0.6154	0.7382	0.9355
0.7919	0.1763	0.9169
0.4103	0.3529	0.1389
0.8936	0.8132	0.2028
0.0579	0.0099	0.1987
0.6038	0.0153	0.9318
0.2722	0.7468	0.4660
0.1988	0.4451	0.4186
0.8462	0.6721	0.6813
0.5252	0.8381	0.3795
0.2026	0.0196	0.8318

Sharing Code

Because the tasks of a job are evaluated on different machines, each machine must have access to all the files needed to evaluate its tasks. The basic mechanisms for sharing code are explained in the following sections:

- "Directly Accessing Files" on page 2-14
- "Passing Data Between Sessions" on page 2-14
- "Passing M-Code for Startup and Finish" on page 2-15

Directly Accessing Files. If the workers all have access to the same drives on the network, they can access needed files that reside on these shared resources. This is the preferred method for sharing data, as it minimizes network traffic.

You must define each worker session's path so that it looks for files in the right places. You can define the path

- By using the job's PathDependencies property. This is the preferred method for setting the path, because it is specific to the job.
- By putting the path command in any of the appropriate startup files for the worker:
 - \$MATLAB\toolbox\local\startup.m file
 - \$MATLAB\toolbox\distcomp\user\jobStartup.m file
 - \$MATLAB\toolbox\distcomp\user\taskStartup.m file.

These files can be passed to the worker by the job's FileDependencies or PathDependencies property. Otherwise, the version of each of these files that is used is the one highest on the worker's path.

Access to files among shared resources can depend upon permissions based on the user name. You can set the user name with which the job manager and worker services of the MATLAB Distributed Computing Engine run by setting the MDCEUSER value in the mdce_def file before starting the services. For Windows systems, there is also MDCEPASS for providing the account password for the specified user. For an explanation of service default settings and the mdce_def file, see "Defining the Script Defaults" in the MATLAB Distributed Computing Engine System Administrator's Guide.

Passing Data Between Sessions. A number of properties on task and job objects are designed for passing code or data from client to job manager to worker, and back. This information could include M-code necessary for task evaluation, or the input data for processing or output data resulting from task evaluation. All these properties are described in detail in their own reference pages:

- InputArguments This property of each task contains the input data provided to the task constructor. This data gets passed into the function when the worker performs its evaluation.
- OutputArguments This property of each task contains the results of the function's evaluation.

- JobData This property of the job object contains data that gets sent to every worker that evaluates tasks for that job. This property works efficiently because the data is passed to a worker only once per job, saving time if that worker is evaluating more than one task for the job.
- FileDependencies This property of the job object lists all the directories and files that get zipped and sent to the workers. At the worker, the data is unzipped, and the entries defined in the property are added to the path of the MATLAB worker session.

The default maximum amount of data that can be sent in a single call for setting properties is approximately 50 MB. This limit applies to the OutputArguments property as well as to data passed into a job. If the limit is exceeded, you get an error message. For information on how to increase this limit, see "Object Data Size Limitations" on page 2-50.

Passing M-Code for Startup and Finish. As a session of MATLAB, a worker session executes its startup.m file each time it starts. You can place the startup.m file in any directory on the worker's MATLAB path, such as toolbox/distcomp/user.

Three additional M-files can initialize and clean up a worker session as it begins or completes evaluations of tasks for a job:

- jobStartup.m automatically executes on a worker when the worker runs its first task of a job.
- taskStartup.m automatically executes on a worker each time the worker begins evaluation of a task.
- taskFinish.m automatically executes on a worker each time the worker completes evaluation of a task.

Empty versions of these files are provided in the directory

```
$MATLAB/toolbox/distcomp/user
```

You can edit these files to include whatever M-code you want the worker to execute at the indicated times.

Alternatively, you can create your own versions of these M-files and pass them to the job as part of the FileDependencies property, or include the path names to their locations in the PathDependencies property.

The worker gives precedence to the versions provided in the FileDependencies property, then to those pointed to in the PathDependencies property. If any of these files is not included in these properties, the worker uses the version of the file in the toolbox/distcomp/user directory of the worker's MATLAB installation.

For further details on these M-files, see the jobStartup, taskStartup, and taskFinish reference pages.

Managing Objects in the Job Manager

Because all the data of jobs and tasks resides in the job manager, these objects continue to exist even if the client session that created them has ended. The following sections describe how to access these objects and how to permanently remove them:

- "What Happens When the Client Session Ends?" on page 2-16
- "Recovering Objects" on page 2-16
- "Permanently Removing Objects" on page 2-18

What Happens When the Client Session Ends? When you close the client session of the Distributed Computing Toolbox, all of the objects in the workspace are cleared. However, the objects in the MATLAB Distributed Computing Engine remain in place. Job objects and task objects reside on the job manager. Local objects in the client session can refer to job managers, jobs, tasks, and workers. When the client session ends, only these local reference objects are lost, not the actual objects in the engine.

Therefore, if you have submitted your job to the job queue for execution, you can quit your client session of MATLAB, and the job will be executed by the job manager. The job manager maintains its job and task objects. You can retrieve the job results later in another client session.

Recovering Objects. A client session of the Distributed Computing Toolbox can access any of the objects in the MATLAB Distributed Computing Engine, whether the current client session or another client session created these objects.

You create job manager and worker objects in the client session by using the findResource function. These client objects refer to sessions running in the engine.

```
jm = findResource('scheduler','type','jobmanager', ...
```

```
'Name', 'Job_Mgr_123', 'LookupURL', 'JobMgrHost')
```

If your network supports multicast, you can find all available job managers by omitting any specific property information.

```
jm_set = findResource('scheduler','type','jobmanager')
```

The array jm_set contains all the job managers accessible from the client session. You can index through this array to determine which job manager is of interest to you.

```
jm = jm_set(2)
```

When you have access to the job manager by the object jm, you can create objects that reference all those objects contained in that job manager. All the jobs contained in the job manager are accessible in its Jobs property, which is an array of job objects.

all_jobs = get(jm,'Jobs')

You can index through the array all_jobs to locate a specific job.

Alternatively, you can use the findJob function to search in a job manager for particular job identified by any of its properties, such as its State.

```
finished_jobs = findJob(jm,'State','finished')
```

This command returns an array of job objects that reference all finished jobs on the job manager jm.

Resetting Callback Properties. When restarting a client session, you lose the settings of any callback properties (for example, the FinishedFcn property) on jobs or tasks. These properties are commonly used to get notifications in the client session of state changes in their objects. When you create objects in a new client session that reference existing jobs or tasks, you must reset these callback properties if you intend to use them.

Permanently Removing Objects

Jobs in the job manager continue to exist even after they are finished, and after the job manager is stopped and restarted. The ways to permanently remove jobs from the job manager are explained in the following sections:

- "Destroying Selected Objects"
- "Starting a Job Manager from a Clean State"

Destroying Selected Objects. From the command line in the MATLAB client session, you can call the destroy function for any job or task object. If you destroy a job, you destroy all tasks contained in that job.

For example, find and destroy all finished jobs in your job manager that belong to the user joep.

The destroy function permanently removes these jobs from the job manager. The clear function removes the object references from the local MATLAB workspace.

Starting a Job Manager from a Clean State. When a job manager starts, by default it starts so that it resumes its former session with all jobs intact. Alternatively, a job manager can start from a clean state with all its former history deleted. Starting from a clean state permanently removes all job and task data from the job manager of the specified name on a particular host.

As a network administration feature, the -clean flag of the job manager startup script is described in "Starting in a Clean State" in the MATLAB Distributed Computing Engine System Administrator's Guide.

Using an LSF Scheduler

If your network already uses a Load Sharing Facility (LSF), you can use the Distributed Computing Toolbox to create jobs to be distributed by your existing scheduler. The following sections provide instructions for using your LSF scheduler:

- "Creating and Running Jobs with an LSF Scheduler" on page 2-19
- "Sharing Code" on page 2-23
- "Managing Objects" on page 2-25

Creating and Running Jobs with an LSF Scheduler

This section details the steps of a typical programming session with the Distributed Computing Toolbox for jobs distributed to workers by an LSF scheduler.

This section assumes you have LSF installed and running on your network. For more information about LSF, see http://www.platform.com/Products/.

The following sections illustrate how to program the Distributed Computing Toolbox to use an LSF scheduler:

- "Find a Scheduler" on page 2-19
- "Create a Job" on page 2-20
- "Create Tasks" on page 2-22
- "Submit a Job to the Job Queue" on page 2-22
- "Retrieve the Job's Results" on page 2-23

Find a Scheduler. You use the findResource function to identify the LSF scheduler and to create an object representing the scheduler in your local MATLAB client session.

You specify 'LSF' as the name for findResource to search for.

```
sched = findResource('scheduler','type','LSF')
```

You set properties on the scheduler object to specify

- Where the job data is stored
- That the workers should access job data directly in a shared file system
- The MATLAB root for the workers to use

```
set(sched,'DataLocation','\\apps\data\project_55')
set(sched,'HasSharedFilesystem',true)
set(sched,'ClusterMatlabRoot','\\apps\matlab\')
```

If DataLocation is not set, the default location for job data is the current working directory of the MATLAB client.

Note In a shared file system, all nodes require access to the directory specified in the scheduler object's DataLocation directory. See the DataLocation reference page for information on setting this property for a mixed-platform environment.

You can look at all the property settings on the scheduler object. If no jobs are in the DataLocation directory, the Jobs property is a 0-by-1 array.

```
get(sched)
DataLocation: '\\apps\data\project_55'
HasSharedFilesystem: 1
Jobs: [Ox1 double]
ClusterMatlabRoot: '\\apps\matlab\'
ClusterName: 'CENTER_MATRIX_CLUSTER'
MasterName: 'masterhost.clusternet.ourdomain.com'
SubmitArguments: ''
```

Create a Job. You create a job with the createJob function, which creates a job object in the client session. The job data is stored in the directory specified by the scheduler object's DataLocation property.

j = createJob(sched)

This statement creates the job object j in the client session. Use get to see the properties of this job object.

```
get(j)

Type: 'job'

Name: 'Job1'

ID: 1

UserName: 'eng1'

Tag: ''

State: 'pending'
```

```
CreateTime: 'Fri Jul 29 16:15:47 EDT 2005'

SubmitTime: ''

FinishTime: ''

Tasks: [0x1 double]

FileDependencies: {0x1 cell}

PathDependencies: {0x1 cell}

JobData: []

Parent: [1x1 distcomp.lsfscheduler]

UserData: []
```

Note that this job using an LSF scheduler has somewhat different properties than a job that uses a job manager. For example, this job has no callback functions.

The job's State property is pending. This state means the job has not been queued for running yet. This new job has no tasks, so its Tasks property is a 0-by-1 array.

The scheduler's Jobs property is now a 1-by-1 array of distcomp.simplejob objects, indicating the existence of your job.

```
get(sched)
```

```
DataLocation: '\\apps\data\project_55'
HasSharedFilesystem: 1
Jobs: [1x1 distcomp.simplejob]
ClusterMatlabRoot: '\\apps\matlab\'
ClusterName: 'CENTRAL_CLUSTER'
MasterName: 'masterhost.clusternet.ourdomain.com'
SubmitArguments: ''
```

You can transfer files to the worker by using the FileDependencies property of the job object. Workers can access shared files by using the PathDependencies property of the job object. For details, see the FileDependencies and PathDependencies reference pages and "Sharing Code" on page 2-13.

Note Properties of a particular job or task should be set from only one computer at a time.

Create Tasks. After you have created your job, you can create tasks for the job. Tasks define the functions to be evaluated by the workers during the running of the job. Often, the tasks of a job are all identical except for different arguments or data. In this example, each task will generate a 3-by-3 matrix of random numbers.

```
createTask(j, @rand, 1, {3,3});
```

The Tasks property of j is now a 5-by-1 matrix of task objects.

```
get(j,'Tasks')
ans =
    distcomp.simpletask: 5-by-1
```

Submit a Job to the Job Queue. To run your job and have its tasks evaluated, you submit the job to the LSF scheduler's job queue.

```
submit(j)
```

The scheduler distributes the tasks of job j to MATLAB workers for evaluation. For each task, the scheduler starts a MATLAB worker session on a worker node; this MATLAB worker session runs for only as long as it takes to evaluate the one task. If the same node evaluates another task in the same job, it does so with a different MATLAB worker session.

The job runs asynchronously. If you need to wait for it to complete before you continue in your MATLAB client session, you can use the waitForState function.

```
waitForState(j)
```

The default state to wait for is finished. This function causes MATLAB to pause until the State property of j is 'finished'.

Note When you use an LSF scheduler in a nonshared file system, the scheduler might report that a job is in the finished state while the job's files might not yet have completed their transfer.

Retrieve the Job's Results. The results of each task's evaluation are stored in that task object's OutputArguments property as a cell array. Use getAllOutputArguments to retrieve the results from all the tasks in the job.

```
results = getAllOutputArguments(j);
```

Display the results from each task.

results{1:5}

0.9501 0.2311	0.4860 0.8913	0.4565 0.0185
0.6068	0.7621	0.8214
0.4447	0.9218	0.4057
0.6154	0.7382	0.9355
0.7919	0.1763	0.9169
0.4103	0.3529	0.1389
0.8936	0.8132	0.2028
0.0579	0.0099	0.1987
0.6038	0.0153	0.9318
0.2722	0.7468	0.4660
0.1988	0.4451	0.4186
0.8462	0.6721	0.6813
0.5252	0.8381	0.3795
0.2026	0.0196	0.8318

Sharing Code

Because different machines evaluate the tasks of a job, each machine must have access to all the files needed to evaluate its tasks. The following sections explain the basic mechanisms for sharing data:

- "Directly Accessing Files" on page 2-24
- "Passing Data Between Sessions" on page 2-24
- "Passing M-Code for Startup and Finish" on page 2-25

Directly Accessing Files. If all the workers have access to the same drives on the network, they can access needed files that reside on these shared resources. This is the preferred method for sharing data, as it minimizes network traffic.

You must define each worker session's path so that it looks for files in the correct places. You can define the path by

- Using the job's PathDependencies property. This is the preferred method for setting the path, because it is specific to the job.
- Putting the path command in any of the appropriate startup files for the worker:
 - \$MATLAB\toolbox\local\startup.m
 - \$MATLAB\toolbox\distcomp\user\jobStartup.m
 - SMATLAB\toolbox\distcomp\user\taskStartup.m

These files can be passed to the worker by the job's FileDependencies or PathDependencies property. Otherwise, the version of each of these files that is used is the one highest on the worker's path.

Passing Data Between Sessions. A number of properties on task and job objects are for passing code or data from client to scheduler or worker, and back. This information could include M-code necessary for task evaluation, or the input data for processing or output data resulting from task evaluation. All these properties are described in detail in their own reference pages:

- InputArguments This property of each task contains the input data provided to the task constructor. This data gets passed into the function when the worker performs its evaluation.
- OutputArguments This property of each task contains the results of the function's evaluation.
- JobData This property of the job object contains data that gets sent to every worker that evaluates tasks for that job.
- FileDependencies This property of the job object lists all the directories and files that get zipped and sent to the workers. At the worker, the data is unzipped, and the entries defined in the property are added to the path of the MATLAB worker session.

Passing M-Code for Startup and Finish. As a session of MATLAB, a worker session executes its startup.m file each time it starts. You can place the startup.m file in any directory on the worker's MATLAB path, such as toolbox/distcomp/user.

Three additional M-files can initialize and clean a worker session as it begins or completes evaluations of tasks for a job:

- jobStartup.m automatically executes on a worker when the worker runs its first task of a job.
- taskStartup.m automatically executes on a worker each time the worker begins evaluation of a task.
- taskFinish.m automatically executes on a worker each time the worker completes evaluation of a task.

Empty versions of these files are provided in the directory

\$MATLAB/toolbox/distcomp/user

You can edit these files to include whatever M-code you want the worker to execute at the indicated times.

Alternatively, you can create your own versions of these M-files and pass them to the job as part of the FileDependencies property, or include the pathnames to their locations in the PathDependencies property.

The worker gives precedence to the versions provided in the FileDependencies property, then to those pointed to in the PathDependencies property. If any of these files is not included in these properties, the worker uses the version of the file in the toolbox/distcomp/user directory of the worker's MATLAB installation.

For further details on these M-files, see the <code>jobStartup</code>, <code>taskStartup</code>, and <code>taskFinish</code> reference pages.

Managing Objects

Objects that the client session uses to interact with the LSF scheduler are only references to data that is actually contained in the directory specified by the DataLocation property. After jobs and tasks are created, you can shut down your client session, restart it, and your job will still be stored in that remote location. You can find existing jobs using the Jobs property of the recreated scheduler object.

The following sections describe how to access these objects and how to permanently remove them:

- "What Happens When the Client Session Ends?" on page 2-26
- "Recovering Objects" on page 2-26
- "Destroying Jobs" on page 2-27

What Happens When the Client Session Ends? When you close the client session of the Distributed Computing Toolbox, all of the objects in the workspace are cleared. However, job objects in the scheduler remain in place. Job and task data remains in the directory identified by DataLocation. When the client session ends, only its local reference objects are lost, not the objects in the scheduler or their data.

Therefore, if you have submitted your job to the scheduler job queue for execution, you can quit your client session of MATLAB, and the job will be executed by the scheduler. The scheduler maintains its job and task objects. You can retrieve the job results later in another client session.

Recovering Objects. A client session of the Distributed Computing Toolbox can access any of the objects in the DataLocation, whether the current client session or another client session created these objects.

You create scheduler objects in the client session by using the findResource function. These objects refer to jobs listed in the scheduler, whose data is found in the specified DataLocation.

```
sched = findResource('scheduler','type','LSF');
set(sched,'DataLocation','/apps/data/project_88');
```

When you have access to the scheduler by the object sched, you can create objects that reference all those objects contained in that scheduler. All the jobs contained in the scheduler are accessible in its Jobs property, which is an array of job objects.

all_jobs = get(sched, 'Jobs')

You can index through the array all_jobs to locate a specific job.

Alternatively, you can use the findJob function to search in a scheduler object for a particular job identified by any of its properties, such as its State.

finished_jobs = findJob(sched,'State','finished')

This command returns an array of job objects that reference all finished jobs on the scheduler sched, whose data is found in the specified DataLocation.

Destroying Jobs. Jobs in the scheduler continue to exist even after they are finished. From the command line in the MATLAB client session, you can call the destroy function for any job object. If you destroy a job, you destroy all tasks contained in that job. The job and task data is deleted from the DataLocation directory.

For example, find and destroy all finished jobs in your scheduler whose data is stored in a specific directory.

```
sched = findResource('scheduler', 'name', 'LSF');
set(sched, 'DataLocation', '/apps/data/project_88');
finished_jobs = findJob(sched, 'State', 'finished');
destroy(finished_jobs);
clear finished_jobs
```

The destroy function permanently removes from the scheduler those jobs whose data is in /apps/data/project_88. The clear function removes the object references from the local MATLAB client workspace.

Using a Generic Scheduler

You can use a generic scheduler to run jobs and distribute tasks to workers. A generic scheduler provides the means to interact with other third-party schedulers, or to create your own scripts for distributing tasks to other nodes on the cluster for evaluation.

The scheduler is a separate application that receives information from your MATLAB client session. With that information, the scheduler starts remote MATLAB worker sessions to evaluate individual tasks of the job. Whereas a job manager keeps MATLAB workers running between tasks, a third-party scheduler runs a MATLAB worker for only as long as it takes the worker to evaluate one task.

However, from the perspective of the MATLAB client, using a generic scheduler is similar to using a job manager or LSF scheduler. You create a scheduler object, jobs, and tasks. Some of the properties of the objects are different, but the theory of running your job is the same. You submit your job to the queue for execution and then retrieve the results. But unlike the MathWorks job manager, which manages the job data for you, a third-party or generic scheduler requires that you manage where job data is stored and assure that all the workers can access it.

The following sections describe how the Distributed Computing Toolbox interacts with your scheduler to run jobs.

- "Programming the Generic Scheduler Object in MATLAB" on page 2-28
- "Using the Submit Function" on page 2-29
- "Using the Decode Function" on page 2-32
- "Running a Job" on page 2-33

Programming the Generic Scheduler Object in MATLAB

This section illustrates how you write a program for running a job with a generic scheduler.

Create a Scheduler Object. You use the findResource function to create an object representing the scheduler in your local MATLAB client session.

You can specify 'generic' as the name for findResource to search for. (Any scheduler name starting with the string 'generic' will create a generic scheduler object.)

```
sched = findResource('scheduler','type','generic')
```

Set Scheduler Object Properties. Generic schedulers must use a shared file system for workers to access job and task data. Set the DataLocation and HasSharedFilesystem properties to specify where the job data is stored, and that the workers should access job data directly in a shared file system.

```
set(sched,'DataLocation','\\apps\data\project_101')
set(sched,'HasSharedFilesystem',true)
```

Note In a shared file system, all nodes require access to the directory specified in the scheduler object's DataLocation directory. See the DataLocation reference page for information on setting this property for a mixed-platform environment.

If DataLocation is not set, the default location for job data is the current working directory of the MATLAB client, which might not be accessible to the worker nodes.

Set the ClusterMatlabRoot property to specify where the MATLAB installation is that the workers are to run for their tasks, if MATLAB is not on the worker's system path.

```
set(sched, 'ClusterMatlabRoot', '\\apps\matlab\')
```

You can look at all the property settings on the scheduler object. If no jobs are in the DataLocation directory, the Jobs property is a 0-by-1 array.

```
get(sched)
DataLocation: '\\apps\data\project_101'
HasSharedFilesystem: 1
Jobs: [Ox1 double]
ClusterMatlabRoot: '\\apps\matlab\'
MatlabCommandToRun: 'matlab -dmlworker -nodisplay -r
distcomp_evaluate_filetask'
Type: 'generic'
SubmitFcn: []
```

You must set the SubmitFcn property to specify the submit function for this job.

```
set(sched,'SubmitFcn',@submitFunc)
```

Using the Submit Function

This section describes the user-defined submit function you use for a generic scheduler. This function, specified by the SubmitFcn property, runs in the MATLAB client when you submit a job to the generic scheduler's queue for execution. Generally, you need only one user-defined submit function for your cluster, and all applications running on that cluster can use the same function.

The user-defined submit function has three purposes:

- To identify the decode function that MATLAB workers run when they start
- To make information about job and task data locations available to the workers via the decode function
- To call the scheduler command to execute a job

Identify the Decode Function. Your submit function that runs on the MATLAB client has a complementary decode function that runs on the MATLAB worker. That decode function is identified in your submit function. For the worker to run the decode function, the function filename must be passed in the environment variable MDCE_DECODE_FUNCTION. This environment variable must exist on the worker computer before the scheduler starts the MATLAB worker session on that computer. The function's location must be on the path of the MATLAB worker.

Pass Location Data to the Worker. When the user-defined submit function is called, it receives at least three arguments: the scheduler object, the job object, and a properties object. (You can use additional arguments if necessary.) Through your submit function, you must make available to the workers some of the information from the properties object. This could be done through shared files, environment variables, or any other means convenient for your configuration.

To see what information is passed into your submit function, type

```
get(distcomp.setprop)
StorageConstructor: ''
StorageLocation: ''
JobLocation: ''
TaskLocations: {0x1 cell}
NumberOfTasks: 0
```

Though the properties appear without any values, you can see what the property names are. In your submit function, you must make the values of these properties available for the decode function that will run from the MATLAB worker session on another node.

Call the Scheduler Command. With properties of the scheduler and job objects, you define the command for your scheduler to run a job. The following example illustrates a command composed in part from properties of the scheduler object and job being run.

Example Submit Function. Following is an example of a user-defined submit function that uses environment variables to pass information into the MATLAB worker sessions. This example runs worker sessions on the same machine. Commonly, you would have your function communicate with a third-party scheduler to distribute the tasks, or you might have your function run worker sessions on remote nodes with something like ssh.

For the complementary decode function, see "Example Decode Function" on page 2-33.

```
function submitFunc(scheduler, job, props, varargin)
% This helper function is used by generic schedulers. It prepares
% the environment for a MATLAB worker, and starts whichever
% MATLAB is first on the path.
% See also workerDecodeFunc.
%
% Assign the relevant values to environment variables, starting
% with identifying the decode function to be run by the worker:
decodeFcn = 'workerDecodeFunc';
dct putenv('MDCE DECODE FUNCTION', decodeFcn);
%
% Set the other job-related environment variables:
dct putenv('MDCE STORAGE LOCATION', props.StorageLocation);
dct putenv('MDCE STORAGE CONSTRUCTOR',props.StorageConstructor);
dct putenv('MDCE JOB LOCATION', props.JobLocation);
%
% Set the task-related variable:
prevDir = cd(fileparts(which(decodeFcn)));
for i = 1:props.NumberOfTasks
     dct putenv('MDCE TASK LOCATION', props.TaskLocations{i});
  % Run a MATLAB worker for each task in the job:
  if ispc
     system(['start ' scheduler.MatlabCommandToRun]);
  else
     logLocation = [scheduler.DataLocation filesep ...
                    props.TaskLocations{i} '.log'];
```

```
system([scheduler.MatlabCommandToRun ' > ' ...
logLocation ' &']);
end
end
cd(prevDir);
```

Using the Decode Function

This section describes the decode function run by the MATLAB worker that receives a task from your generic scheduler. The purpose of the decode function is to receive information from the scheduler about job and task data locations.

The decode function must be on the path of the MATLAB worker. It runs in the MATLAB worker as soon as that session begins. Generally, you need only one decode function for your cluster, and all applications running on that cluster can use the same function.

Because the scheduler object's submit function identifies the decode function, the decode and submit functions complement each other. That is, the decode function complies with the data transfer means defined in the submit function.

The decode function has an output argument that is an object whose properties reflect the information necessary for the MATLAB worker to evaluate its assigned task. To see the properties of this object, type

get(distcomp.runprop)

```
StorageConstructor: ''
StorageLocation: ''
JobLocation: ''
TaskLocation: ''
DependencyDirectory: 'C:\Temp\tmp12345'
HasSharedFilesystem: 1
```

The decode function must set the property values with data received from the complementary submit function, by whatever means data was made available. (The DependencyDirectory property is optional. This allows you to define where the FileDependencies are unzipped on the worker, as opposed to using the default location.)

Example Decode Function. Following is an example decode function that complements the user-defined submit function in the previous example. Because that submit function made the properties available as environment variables, this corresponding decode function reads the values of those environment variables and returns them to the MATLAB worker session.

For the complementary submit function, see "Example Submit Function" on page 2-31.

function workerDecodeFunc(runprop)

```
% This function is referenced by SubmitFunc. If a generic
% scheduler has been created with SubmitFcn = 'submitFunc', this
\% function will be called on the MATLAB workers started by that
% generic scheduler.
% THIS FUNCTION MUST BE ON THE PATH OF THOSE MATLAB WORKERS;
% typically, this is accomplished by changing to the directory
% where this function is, before starting those MATLAB workers.
%
% Read environment variables into local variables. The names of
% the environment variables were determined by submitFunc.
storageConstructor = getenv('MDCE STORAGE CONSTRUCTOR');
storageLocation = getenv('MDCE STORAGE LOCATION');
jobLocation = getenv('MDCE JOB LOCATION');
taskLocation = getenv('MDCE TASK LOCATION');
% Set runprop properties from the local variables:
set(runprop, ...
    'StorageConstructor', storageConstructor, ...
    'StorageLocation', storageLocation, ...
    'JobLocation', jobLocation, ....
    'TaskLocation', taskLocation);
```

Running a Job

This section illustrates the running of a job on your generic scheduler from the MATLAB client session. With the scheduler running and the user-defined submit and decode functions defined, running a job is now similar to running with a job manager or any other type of scheduler.

Create a Job. You create a job with the createJob function, which creates a job object in the client session. The job data is stored in the directory specified by the scheduler object's DataLocation property.

```
j = createJob(sched)
```

This statement creates the job object j in the client session. Use get to see the properties of this job object.

```
get(j)
```

```
Type: 'job'
            Name: 'Job1'
              ID: 1
        UserName: 'neo'
                   1.1
             Tag:
           State: 'pending'
      CreateTime: 'Fri Jul 29 16:15:47 EDT 2005'
      SubmitTime: ''
       StartTime: ''
      FinishTime: ''
           Tasks: [0x1 double]
FileDependencies: {0x1 cell}
PathDependencies: {0x1 cell}
         JobData: []
          Parent: [1x1 distcomp.genericscheduler]
        UserData: []
```

Note Properties of a particular job or task should be set from only one computer at a time.

Note that this generic scheduler job has somewhat different properties than a job that uses a job manager. For example, this job has no callback functions.

The job's State property is pending. This state means the job has not been queued for running yet. This new job has no tasks, so its Tasks property is a 0-by-1 array.

The scheduler's Jobs property is now a 1-by-1 array of distcomp.simplejob objects, indicating the existence of your job.

Create Tasks. After you have created your job, you can create tasks for the job. Tasks define the functions to be evaluated by the workers during the running of the job. Often, the tasks of a job are all identical except for different arguments or data. In this example, each task will generate a 3-by-3 matrix of random numbers.

```
createTask(j, @rand, 1, {3,3});
```

The Tasks property of j is now a 5-by-1 matrix of task objects.

```
get(j,'Tasks')
ans =
    distcomp.simpletask: 5-by-1
```

Submit a Job to the Job Queue. To run your job and have its tasks evaluated, you submit the job to the scheduler's job queue.

```
submit(j)
```

The scheduler distributes the tasks of j to MATLAB workers for evaluation.

The job runs asynchronously. If you need to wait for it to complete before you continue in your MATLAB client session, you can use the waitForState function.

```
waitForState(j)
```

The default state to wait for is finished or failed. So this function causes MATLAB to pause until the State property of j is 'finished' or 'failed'.

Retrieve the Job's Results. The results of each task's evaluation are stored in that task object's OutputArguments property as a cell array. Use getAllOutputArguments to retrieve the results from all the tasks in the job.

results = getAllOutputArguments(j);

Display the results from each task.

results{1:5}

0.9501 0.2311	0.4860 0.8913	0.4565 0.0185
0.6068	0.7621	0.8214
0.4447	0.9218	0.4057
0.6154	0.7382	0.9355
0.7919	0.1763	0.9169
0.4103	0.3529	0.1389
0.8936	0.8132	0.2028
0.0579	0.0099	0.1987
0.6038	0.0153	0.9318
0.2722	0.7468	0.4660
0.1988	0.4451	0.4186
0.8462	0.6721	0.6813
0.5252	0.8381	0.3795
0.2026	0.0196	0.8318

Programming Parallel Jobs

A parallel job consists of only a single task that runs simultaneously on several workers. More specifically, the task is duplicated on each worker, so each worker can perform the task on a different set of data, or on a particular segment of a large data set. The workers can communicate with each other as each executes its task. In this configuration, workers are referred to as *labs*.

In principle, creating and running parallel jobs is similar to programming distributed jobs:

- 1 Find a scheduler
- 2 Create a parallel job
- **3** Create a task
- 4 Submit the job for running
- **5** Retrieve results

The differences between distributed jobs and parallel jobs are summarized in the following table.

Distributed Job	Parallel Job
MATLAB sessions, called <i>workers</i> , perform the tasks but do not communicate with each other.	MATLAB sessions, called <i>labs</i> , can communicate with each other during the running of their tasks.
You define any number of tasks in a job.	You define only one task in a job. Duplicates of that task run on all labs running the parallel job.

Distributed Job	Parallel Job
Tasks need not run simultaneously. Tasks are distributed to workers as the workers become available, so a worker can perform several of the tasks in a job.	Tasks run simultaneously, so you can run the job only on as many labs as are available at run time. The start of the job might be delayed until the required number of labs is available.
Supported by any type of scheduler.	Supported only by mpiexec schedulers and the MathWorks job manager.

A parallel job has only one task that runs simultaneously on every lab. The function that the task runs can take advantage of a lab's awareness of how many labs are running the job, which lab this is among those running the job, and the features that allow labs to communicate with each other.

The following sections describe how to program parallel jobs:

- "Using a Job Manager" on page 2-38
- "Using an mpiexec Scheduler" on page 2-40
- "Further Notes on Parallel Jobs" on page 2-43

Using a Job Manager

You can run a parallel job using the job manager or an mpiexec scheduler. This section illustrates a parallel job programmed for the job manager.

Coding the Task Function

In this example, the lab whose labindex value is 1 creates a magic square comprised of a number of rows and columns that is equal to the number of labs running the job. More specifically, four labs run a parallel job with a 4-by-4 magic square. The first lab broadcasts the matrix to all the other labs, each of which calculates the sum of one column of the matrix. All of these column sums are combined to calculate the total sum of the elements of the original magic square.

The function for this example is shown below.

```
function total_sum = colsum
if labindex == 1
```

```
% Send magic square to other labs
A = labBroadcast(1,magic(numlabs))
else
% Receive broadcast on other labs
A = labBroadcast(1)
end
% Calculate sum of column identied by labindex for this lab
column_sum = sum(A(:,labindex))
% Calculate total sum by combining column sum from all labs
total_sum = gop(@plus, column_sum)
```

This function is saved as the file colsum.m on the path of the MATLAB client. It will be sent to each lab by the job's FileDependencies property.

While this example has one lab create the magic square and broadcast it to the other labs, there are alternative methods of getting data to the labs. In this case, each lab could create the matrix for itself. Alternatively, each lab could read its part of the data from a common file, the data could be passed in as an argument to the task function, or the data could be sent in a file contained in the job's FileDependencies property. The solution you choose will depend on your network configuration and the nature of the data.

Coding in the Client

As with distributed jobs, you find a scheduler and create a scheduler object in your MATLAB client by using the findResource function.

```
jm = findResource('scheduler','type','jobmanager', ...
'name','MyJobManager','LookupURL','jobman host')
```

You create the job with the createParallelJob function.

```
pjob = createParallelJob(jm);
```

To run the job on four labs, set the job's properties that limit the number of workers.

```
set(pjob,'MinimumNumberOfWorkers',4)
set(pjob,'MaximumNumberOfWorkers',4)
```

The function file colsum.m is on the MATLAB client path, but it has to be made available to the labs. One way to do this is with the job's FileDependencies property.

```
set(pjob, 'FileDependencies', {'colsum.m'})
```

You create the job's one task with the usual createTask function. In this example, the task returns only one argument from each lab, and there are no input arguments to the colsum function.

```
t = createTask(pjob, @colsum, 1, {})
```

Use submit to run the job.

```
submit(pjob)
```

Make the MATLAB client wait for the job to finish before collecting the results. The results consist of one value from each lab. The gop function in the task shares data between the labs, so that each lab has the same result.

```
waitForState(pjob)
results = getAllOutputArguments(pjob)
results =
   [136]
   [136]
   [136]
   [136]
```

Using an mpiexec Scheduler

Parallel jobs can run on an mpiexec scheduler. You might already have access to an mpiexec scheduler on your cluster, or your administrator can set one up using the mpiexec software included with the MATLAB Distributed Computing Engine.

This example estimates the value of pi by dividing up the integration of the function $4/(1 + x^2)$ over the range 0 to 1. The task function can accommodate any number of labs, but in this example the client code specifies the number of labs as 4.

Coding the Task Function

In this example, the task function requires no input arguments. As a lab runs the task, it is aware of how many labs are running the job, and divides the total integration interval into a number of subintervals. So, if you use four labs, each lab integrates one-fourth of the entire integral. The total number of labs is identified by the value numlabs, while each lab performing a task for this job has a unique labindex, starting with 1, 2, etc. In this example, numlabs is 4, and the values of labindex are 1, 2, 3, and 4.

When all the labs have finished calculating their own portions of the integral, labs 2, 3, and 4 use the labSend function to transfer their results to lab 1, which collects this data with the labReceive function.

```
function piApprox = quadpi
% QUADPI
         Approximate pi via parallel numerical quadrature.
%
    Copyright 2005 The MathWorks, Inc.
% Approximate pi by the numerical integral
% of F = 4/(1 + x^2) from 0 to 1.
F = Q(x)4./(1 + x.^2);
% Each lab calculates the integral of F over a
% subinterval [a, b] of [0, 1].
a = (labindex - 1)/numlabs;
b = labindex/numlabs;
% Use a built-in MATLAB guadrature method to approximate
% the integral.
myIntegral = quadl(F,a,b);
% The labs have now all calculated their portions of the
% integral of F, and will all send their results to lab 1, which
% will add them together to form the entire integral over [0, 1].
if (labindex == 1)
    % Receive the integral contribution from all the other labs.
    piApprox = myIntegral;
    for otherLab = 2:numlabs
        piApprox = piApprox + labReceive(otherLab);
    end
else
    % Send the integral contribution to lab 1.
```

```
piApprox = [];
labSend(myIntegral, 1);
end
```

Coding in the Client

To create a job for the mpiexec scheduler, first use findResource to find the scheduler and create a scheduler object. Then set the scheduler object properties with values appropriate for your network configuration.

Create a parallel job.

pjob = createParallelJob(sched);

Set the number of workers for the job to run on. This example uses exactly four workers, but you can use any number of workers that are simultaneously available to you.

```
set(pjob, 'MaximumNumberOfWorkers', 4);
set(pjob, 'MinimumNumberOfWorkers', 4);
```

Define the task of the parallel job with createTask. You create only one task, but the toolbox duplicates it to run simultaneously on all the workers (labs).

The file quadpi.m must be available to all the workers. It could be passed in the job's FileDependencies property, but in this example it is in a directory on the path of each of the workers, so the client code shown here does not have to mention the file or its location. Note that the task returns only one argument (the value of its portion of the integration), and that it has no input arguments (the empty cell array).

```
createTask(pjob, @quadpi, 1, {});
```

Use submit to run the job.

submit(pjob);

Make the MATLAB client wait for the job to finish before collecting the results.

```
waitForState(pjob, 'finished');
```

The result consists of the sum of the values from all of the labs, as collected by lab 1. The example compares its result to the built-in value of pi.

```
data = getAllOutputArguments(pjob);
piApprox = data{1};
fprintf('pi is approximately %.15f.\n', piApprox);
fprintf('Error is %g.\n', abs(pi - piApprox));
```

Further Notes on Parallel Jobs

Though you create only one task for a parallel job, the system creates additional identical tasks for each worker. So if a parallel job runs on four workers (labs), when the job is run, the Tasks property of the job will contain four task objects.

The first task in the job's Tasks property corresponds to the task run by the lab whose labindex is 1. If there is some unique code for one of the labs, or if you need to be able to identify the results from a particular lab, you should use labindex == 1 for that purpose.

For other labs, there is no correspondence to the sequence of objects in the Tasks property and the labindex value of the labs. However, the order of those tasks in the Tasks property does correspond to the sequence of results in the OutputArguments property and with those returned by the getAllOutputArguments function.

Programming with User Configurations

Configurations allow you to define certain parameters and properties in an M-file, then have that file provide your settings when creating objects in the MATLAB client. The functions that support the use of configurations are

- createJob
- createParallelJob
- createTask
- dfeval
- dfevalasync
- findResource
- set

The following sections describe how to define and apply user configurations:

- "Defining Configurations" on page 2-44
- "Applying Configurations in Client Code" on page 2-45

Defining Configurations

The Distributed Computing Toolbox includes a file called \$MATLAB/toolbox/distcomp/user/distcompUserConfig.m. To use configurations, you should copy this file to a directory that is higher on your MATLAB path than \$MATLAB/toolbox/distcomp/user, and edit your copy so that it accurately reflects your scheduler and how you want to run your jobs.

The file contains configurations for each type of scheduler supported by the toolbox. Each configuration takes the name of the subfunction in which it is defined. For each configuration, there are listed several parameters or properties that you can set, arranged by object type. You can also add your own configuration to the file by following the instructions included in the file.

Example - Setting Properties in the User Configuration File

Suppose you want to set several properties for a job being run by a job manager. In the distcompUserConfig.m file, you edit the configuration called jobmanager.

Find the section of the file identified by the line

```
function conf = jobmanager()
```

In that section is a block of code that reads

```
% Job properties
conf.job.PathDependencies = {};
conf.job.FileDependencies = {};
% The following job properties are specific to the job manager
conf.job.RestartWorker = false;
conf.job.MaximumNumberOfWorkers = inf;
conf.job.MinimumNumberOfWorkers = 1;
conf.job.Timeout = inf;
```

To set the maximum and minimum number of workers and the timeout for a job, edit the last three line in this section. For example,

```
conf.job.MaximumNumberOfWorkers = 4;
conf.job.MinimumNumberOfWorkers = 4;
conf.job.Timeout = 180;
```

When this configuration is applied to a job object, the job will run only on 4 workers, and have a timeout of 3 minutes.

Applying Configurations in Client Code

In the MATLAB client where you create and define your distributed computing objects, you can use configurations when creating the objects, or you can apply configurations to objects that already exist.

Finding Schedulers

When calling the findResource function, you can use configurations to identify a particular scheduler. For example,

```
jm = findResource('scheduler','configuration','jobmanager')
```

This command finds the scheduler defined by the settings of the jobmanager configuration in the distcompUserConfig.m file. The advantage of configurations is that you can alter your schedule choices without changing your MATLAB application code. To accommodate different schedulers, the file includes configurations called jobmanager, lsf, mpiexec, and generic. You can also add your own configurations to the file.

For third-party schedulers, settable object properties can be defined in the configuration and applied after findResource has created the scheduler object.

Setting Job and Task Properties

You can set the properties of a job or task with configurations when you create the objects, or you can apply a configuration after you create the object. The following code creates and configures two jobs with the same property values.

```
job1 = createJob(jm,'Configuration','jobmanager')
job2 = createJob(jm)
set(job2,'Configuration','jobmanager')
```

Notice that the Configuration property of a job indicates the configuration that was applied to the job.

```
get(job1,'Configuration')
    jobmanager
```

When you apply a configuration to an object, all the properties defined in that configuration section of the distcompUserConfig.m file get applied to the object, and the object's Configuration property is set to reflect the name of the configuration that you applied. If you later change any of the job's properties that had been set by that configuration, the job's configuration property is cleared.

Programming Tips and Notes

This section provides programming tips that might enhance your program performance.

Saving or Sending Objects

Do not use the save or load functions on Distributed Computing Toolbox objects. Some of the information that these objects require is stored in the MATLAB session persistent memory and would not be saved to a file.

Similarly, you cannot send a distributed computing object between distributed computing processes by means of an object's properties. For example, you cannot pass a job manager, job, task, or worker object to MATLAB workers as part of a job's JobData property.

Current Working Directory of MATLAB Worker

The current directory of a MATLAB worker at the beginning of its session is

CHECKPOINTBASE\HOSTNAME_WORKERNAME_mlworker_log\work

where CHECKPOINTBASE is defined in the mdce_def file, HOSTNAME is the name of the node on which the worker is running, and WORKERNAME is the name of the MATLAB worker session.

For example, if the worker named worker22 is running on host nodeA52, and its CHECKPOINTBASE value is C:\TEMP\MDCE\Checkpoint, the starting current directory for that worker session is

 $\verb|C:\TEMP\MDCE\Checkpoint\nodeA52_worker22_mlworker_log\worker\Checkpoint\nodeA52_worker22_mlworker_log\Norker\Checkpoint\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker22_mlworker\NodeA52_worker24_mlworker\NodeA54_$

Using clear functions

Executing

clear functions

clears all Distributed Computing Toolbox objects from the current MATLAB session. They still remain in the job manager. For information on recreating these objects in the client session, see "Recovering Objects" on page 2-16.

Running Tasks That Call Simulink

The first task that runs on a worker session that uses Simulink[®] can take a long time to run, as Simulink is not automatically started at the beginning of the worker session. Instead, Simulink starts up when first called. Subsequent tasks on that worker session will run faster, unless the worker is restarted between tasks.

Using the pause Function

On worker sessions running on Macintosh or UNIX machines, pause(inf) returns immediately, rather than pausing. This is to prevent a worker session from hanging when an interrupt is not possible.

Transmitting Large Amounts of Data

Operations that involve transmitting many objects or large amounts of data over the network can take a long time. For example, getting a job's Tasks property or the results from all of a job's tasks can take a long time if the job contains many tasks.

Interrupting a Job

Because jobs and tasks are run outside the client session, you cannot use Ctrl+C (^C) in the client session to interrupt them. To control or interrupt the execution of jobs and tasks, use such functions as cancel, destroy, demote, promote, pause, and resume.

IPv6 on Macintosh

To allow multicast access between different distributed computing processes run by different users on the same Macintosh computer, IPv6 addressing is disabled for MATLAB with the Distributed Computing Toolbox on a Macintosh.

Speeding Up a Job

You might find that your code runs slower on multiple workers than it does on one desktop computer. This can occur when task startup and stop time is not negligible relative to the task run time. The most common mistake in this regard is to make the tasks too small, i.e., too fine-grained. Another common mistake is to send large amounts of input or output data with each task. In both of these cases, the time it takes to transfer data and initialize a task is far greater than the actual time it takes for the worker to evaluate the task.

Troubleshooting and Debugging

Object Data Size Limitations

By default, the size limit of data transfers among the distributed computing objects is approximately 50 MB, determined by the Java Virtual Machine (JVM) memory allocation limit. You can increase the amount of JVM memory available to the distributed computing processes (clients, job manager, and workers).

MATLAB Clients and Workers

You can find the current maximum JVM memory limit by typing the command

```
java.lang.Runtime.getRuntime.maxMemory
ans =
    98172928
```

MATLAB clients and MATLAB workers allow up to approximately half of the JVM memory limit for large data transfers. In the default case, half of the approximately 100-MB limit is about 50 MB.

To increase the limit, create a file named java.opts that includes the -Xmx option, specifying the amount of memory you want to give the JVM.

For example, to increase the JVM memory allocation limit to 200 MB, use the following syntax in the java.opts file:

-Xmx200m

This increased limit allows approximately 100 MB of data to be transferred with distributed computing objects.

Note To avoid virtual memory thrashing, never set the -Xmx option to more than 66% of the physical RAM available.

For MATLAB clients on UNIX or Macintosh systems, place the java.opts file in a directory where you intend to start MATLAB, and move to that directory before starting MATLAB.

For MATLAB clients on Windows systems

- 1 Create the java.opts file in a directory where you intend to start MATLAB.
- **2** Create a shortcut to MATLAB.
- 3 Right-click the shortcut and select Properties.
- **4** In the Properties dialog box, specify the name of the directory in which you created the java.opts file as the MATLAB startup directory.

For computers running MATLAB workers, place the modified java.opts file in

\$MATLAB/toolbox/distcomp/bin (for UNIX or Macintosh)
\$MATLAB\toolbox\distcomp\bin\win32 (for Windows)

Job Managers

For job managers, the Java memory allocation limit is set in the mdce_def file.

This file can be found at

\$MATLAB/toolbox/distcomp/bin/mdce_def.sh (for UNIX or Macintosh)
\$MATLAB\toolbox\distcomp\bin\win32\mdce_def.bat (for Windows)

The parameter in this file controlling the Java memory limit is JOB_MANAGER_MAXIMUM_MEMORY. You should set this limit to 4 times the value you need for data transfers in your job. For example, to accommodate data transfers of 100 MB, modify the line for UNIX or Macintosh to read

```
JOB_MANAGER_MAXIMUM_MEMORY="400m"
```

Or for Windows, to read

set JOB_MANAGER_MAXIMUM_MEMORY=400m

Note Although you can increase the amount of data that you can transfer between objects, it is probably more efficient to have the distributed computing processes directly access large data sets in a shared file system. See "Directly Accessing Files" on page 2-14.

File Access and Permissions

Ensuring that Windows Workers Can Access Files

By default, a worker on a Windows node is installed as a service running as LocalSystem, so it does not have access to mapped network drives.

Often a network is configured to not allow services running as LocalSystem to access UNC or mapped network shares. In this case, you must run MDCE under a different user with rights to log on as a service. See the section "Setting the User" in the MATLAB Distributed Computing Engine System Administrator's Guide.

Task Function Unavailable

If a worker cannot find the task function, it returns the error message

```
Error using ==> feval
Undefined command/function 'function_name'.
```

The worker that ran the task did not have access to the function function_name. One solution is to make sure the location of the function's file, function_name.m, is included in the job's PathDependencies property. Another solution is to transfer the function file to the worker by adding function_name.m to the FileDependencies property of the job.

Load and Save Errors

If a worker cannot save or load a file, you might see the error messages

```
??? Error using ==> save
Unable to write file myfile.mat: permission denied.
??? Error using ==> load
Unable to read file myfile.mat: No such file or directory.
```

In determining the cause of this error, consider the following questions:

- What is the worker's current directory?
- Can the worker find the file or directory?
- What user is the worker running as?
- Does the worker have permission to read or write the file in question?

Tasks or Jobs Remain in Queued State

A job or task might get stuck in the queued state. To investigate the cause of this problem, look for the scheduler's logs:

- LSF might send e-mails with error messages.
- An mpiexec scheduler saves output messages in its debug log.
- If using a generic scheduler, make sure the submit function redirects error messages to a log file.

Possible causes of the problem are

- MATLAB failed to start due to licensing errors, is not on the default path on the worker, or is not installed in the location where the scheduler expected it to be.
- MATLAB could not read/write the job input/output files in the scheduler's data location. The data location may not be accessible to all the worker nodes, or the user that MATLAB runs as does not have permission to read/write the job files.
- If using a generic scheduler
 - The environment variable MDCE_DECODE_FUNCTION was not defined before the MATLAB worker started.
 - The decode function was not on the worker's path.
- If using mpiexec
 - The passphrase to smpd was incorrect or missing.
 - The smpd daemon was not running on all the specified machines.

No Results from Job

Task Errors

If your job returned no results (i.e., getAllOutputArguments(job) returns an empty cell array), it is probable that the job failed and some of its tasks have their ErrorMessage and ErrorIdentifier properties set.

You can use the MATLAB property inspector to search for these tasks.

inspect(yourjob);

Alternatively, you can use the following code to identify tasks with error messages:

```
errmsgs = get(yourjob.Tasks, {'ErrorMessage'});
nonempty = ~cellfun(@isempty, errmsgs);
celldisp(errmsgs(nonempty));
```

This code displays the nonempty error messages of the tasks found in the job object your job.

Connection Problems Between Client and Job Manager

Detailed instructions for diagnosing connection problems between the client and job manager can be found in some of the Bug Reports listed on the MathWorks Web site. The following sections can help you identify the general nature of some connection problems.

Client Cannot See Job Manager

If you cannot locate your job manager with

```
findResource('scheduler','type','jobmanager')
```

the most likely reasons for this failure are

• The client cannot contact the job manager host via multicast. Try to fully specify where to look for the job manager by using the LookupURL property in your call to findResource:

- The job manager is currently not running.
- Firewalls do not allow traffic from the client to the job manager.
- The client and the job manager are not running the same version of the software.

Job Manager Cannot See Client

If findResource displays a warning message that the job manager cannot open a TCP connection to the client computer, the most likely reasons for this are

- Firewalls do not allow traffic from the job manager to the client.
- The job manager cannot resolve the short hostname of the client computer. Use dctconfig to change the hostname that the job manager will use for contacting the client.

3

Function Reference

This chapter describes the Distributed Computing Toolbox M-file functions that you use directly to evaluate MATLAB code in a cluster of computers.

Functions — Categorical
List (p. 3-2)Contains a series of tables that group functions by categoryFunctions — Alphabetical
List (p. 3-6)Lists all the functions alphabetically

Functions – Categorical List

This section contains descriptions of all the Distributed Computing Toolbox commands and functions.

General Functions	Distributed Computing Toolbox functions not specific to a particular object type
Job Manager Functions	Functions that operate on a job manager object
Job Functions	Functions that operate on a job object
Task Functions	Functions that operate on a task object
Worker Functions	Functions that are meaningful only within a MATLAB worker session

General Functions

clear	Remove objects from MATLAB workspace
dctconfig	Configure settings for Distributed Computing Toolbox client session
dfeval	Evaluate function using a cluster of computers
dfevalasync	Evaluate function asynchronously using a cluster of computer
findResource	Find available distributed computing resources
get	Return object properties
help	Display help for toolbox functions in Command Window
inspect	Open the Property Inspector
jobStartup	Job startup M-file for user-defined options
length	Return length of object array
methods	List functions of object class
set	Configure or display object properties
size	Return size of object array

taskFinish	Task finish M-file for user-defined options
taskStartup	Task startup M-file for user-defined options

Job Manager Functions

createJob	Create job object
createParallelJob	Create parallel job object
demote	Demote job in job manager queue
findJob	Find job objects stored in job queue
pause	Pause job manager queue
promote	Promote job in job manager queue
resume	Resume processing queue in job manager

Scheduler Functions

createJob	Create job object
createParallelJob	Create parallel job object
getDebugLog	Return output messages from parallel job run by mpiexec scheduler
mpiLibConf	Return location of MPI implementation
mpiSettings	Set options for MPI communication

Job Functions

cancel	Cancel a pending, queued, or running job
createTask	Create new task in job
destroy	Remove job object from a job manager and memory
findTask	Get task objects belonging to job object
getAllOutputArguments	Retrieve output arguments from all tasks evaluated in job object

submit	Queue job in job queue service
waitForState	Wait for job object to change state

Parallel Job Functions

In addition to the functions of a job, parallel jobs also support the following functions.

createParallelJob	Create parallel job object. (This is a scheduler function.)
gop	Perform global operation across all labs
labBarrier	Block execution until all labs have reached this call
labBroadcast	Send data to all labs or receive data sent to all labs
labindex	Return ID of this lab
labProbe	Test to see if messages are ready for labReceive
labReceive	Receive data from another lab
labSend	Send data to another specified lab
numlabs	Return total number of labs operating in parallel on same job

Task Functions

cancel	Cancel a pending or running task
destroy	Remove task object from job and from memory
waitForState	Wait for task object to change state

Worker Functions

These functions operate only within a worker session of MATLAB.

getCurrentJob	Get job object whose task is currently being evaluated
getCurrentJobmanager	Get job manager object that distributed current task
getCurrentTask	Get task object currently being evaluated in this worker session
getCurrentWorker	Get worker object currently running this session

Functions – Alphabetical List

This section contains detailed descriptions of the Distributed Computing Toolbox functions. Each function reference page contains some or all of the following information:

- The function name
- The function purpose
- The function syntax

Valid input argument and output argument combinations are shown. In some cases, an ellipsis (\ldots) is used for the input arguments. This means that all preceding input argument combinations are valid for the specified output argument(s).

- A description of each argument
- A description of each function syntax
- Additional remarks about usage
- An example of usage
- Related functions and properties

Purpose	Cancel a pending or running task, or cancel a pending, queued, or running job
Syntax	cancel(t) cancel(j)
Arguments	tPending or running task to cancel.jPending, running, or queued job to cancel.
Description	 cancel(t) stops the task object, t, that is currently in the pending or running state. The task's State property is set to finished, and no output arguments are returned. An error message stating that the task was canceled is placed in the task object's ErrorMessage property, and the worker session running the task is restarted. cancel(j) stops the job object, j, that is pending, queued, or running. The job's State property is set to finished, and a cancel is executed on all tasks in the job that are not in the finished state. A job object that has been canceled cannot be started again. If the job is running in a job manager, any worker sessions that are evaluating tasks belonging to the job object will be restarted.
Example	Cancel a task. Note afterward the task's State, ErrorMessage, and OutputArguments properties. job1 = createJob(jm); t = createTask(job1, @rand, 1, {3,3}); cancel(t) get(t) ID: 1 Function: @rand NumberOfOutputArguments: 1 InputArguments: {[3] [3]} OutputArguments: {1x0 cell} CaptureCommandWindowOutput: 0 CommandWindowOutput: '' State: 'finished' ErrorMessage: 'Task cancelled by user' ErrorIdentifier: 'dce:task:cancelled'

Timeout: Inf CreateTime: 'Fri Oct 22 11:38:39 EDT 2004' StartTime: 'Fri Oct 22 11:38:46 EDT 2004' FinishTime: 'Fri Oct 22 11:38:46 EDT 2004' Worker: [] Parent: [1x1 distcomp.job] UserData: [] RunningFcn: [] FinishedFcn: []

See Also destroy, submit

Purpose	Remove objects from MATLAB workspace	
Syntax	clear obj	
Arguments	obj An object or an array of objects.	
Description	clear obj removes obj from the MATLAB workspace.	
Remarks	If obj references an object in the job manager, it is cleared from the workspace, but it remains in the job manager. You can restore obj to the workspace with the findResource, findJob, or findTask function; or with the Jobs or Tasks property.	
Example	This example creates two job objects on the job manager jm. The variables for these job objects in the MATLAB workspace are job1 and job2. job1 is copied to a new variable, job1copy; then job1 and job2 are cleared from the MATLAB workspace. The job objects are then restored to the workspace from the job object's Jobs property as j1 and j2, and the first job in the job manager is shown to be identical to job1copy, while the second job is not.	
	<pre>job1 = createJob(jm); job2 = createJob(jm); job1copy = job1; clear job1 job2; j1 = jm.Jobs(1); j2 = jm.Jobs(2); isequal (job1copy, j1) ans =</pre>	
See Also	createJob, createTask, findJob, findResource, findTask	

createJob

Purpose	Create job object in scheduler and client	
Syntax	obj = createJob(scheduler) obj = createJob(, ' <i>p1</i> ', v1, ' <i>p2</i> ', v2,) obj = createJob(, ' configuration ', 'ConfigurationName',)	
Arguments	obj	The job object.
	scheduler	The job manager object representing the job manager service that will execute the job, or the scheduler object representing the scheduler on the cluster that will distribute the job.
	p1, p2	Object properties configured at object creation.
	v1, v2	Initial values for corresponding object properties.
Description		scheduler) creates a job object at the data location for the er, or in the job manager.
	obj = createJob(, $p1'$, v1, $p2'$, v2,) creates a job object with the specified property values. If an invalid property name or property value is specified, the object will not be created.	
	Note that the property value pairs can be in any format supported by the set function, i.e., param-value string pairs, structures, and param-value cell array pairs. If a structure is used, the structure field names are job object property names and the field values specify the property values.	
		hird-party scheduler instead of a job manager, the job's data ation specified by the job's DataLocation property.
	creates a job object ConfigurationNam distcompUserConf	, 'configuration', 'ConfigurationName',) t with the property values specified in the configuration ne. Configurations are defined in the file 'ig.m. For details about writing and applying configurations, with User Configurations" on page 2-44.

createJob

Example Construct a job object. jm = findResource('scheduler', 'type', 'jobmanager', ... 'name', 'MyJobManager', 'LookupURL', 'JobMgrHost'); obj = createJob(jm, 'Name', 'testjob'); Add tasks to the job. for i = 1:10createTask(obj, @rand, 1, {10}); end Run the job. submit(obj); Retrieve job results. out = getAllOutputArguments(obj); Display the random matrix. disp(out{1}{1}); Destroy the job. destroy(obj); See Also createParallelJob, createTask, findJob, findResource, submit

createParallelJob

Purpose	Create parallel job object		
Syntax	<pre>pjob = createParallelJob(scheduler) pjob = createParallelJob(, 'p1', v1, 'p2', v2,) pjob = createParallelJob(, 'configuration', 'ConfigurationName')</pre>		
Arguments	pjob scheduler p1,p2	The parallel job object. The scheduler object created by findResource, using either a job manager or mpiexec scheduler. Object properties configured at object creation.	
	v1, v2	Initial values for corresponding object properties.	
Description	<pre>pjob = createParallelJob(scheduler) creates a parallel job object at the data location for the identified scheduler, or in the job manager. Future modifications to the job object result in a remote call to the job manager or modification to data at the scheduler's data location. pjob = createParallelJob(, 'p1', v1, 'p2', v2,) creates a</pre>		
	parallel job obje	parallel job object with the specified property values. If an invalid property name or property value is specified, the object will not be created.	
	Note that the property value pairs can be in any format supported by the set function, i.e., param-value string pairs, structures, and param-value cell array pairs.		
	'Configuratio values specified defined in the f	ParallelJob(, ' configuration ', nName',) creates a parallel job object with the property l in the configuration ConfigurationName. Configurations are ile distcompUserConfig.m. For details about writing and urations, see "Programming with User Configurations" on	
Example	jm = findRe	rallel job object in a job manager queue. esource('scheduler','type','jobmanager'); ateParallelJob(jm,'Name','testparalleljob'); the job.	

```
createTask(pjob, 'rand', 1, {3});
```

Set the number of workers required for parallel execution.

```
set(pjob,'MinimumWorkers',3);
set(pjob,'MaximumWorkers',3);
```

Run the job.

submit(pjob);

Retrieve job results.

waitForState(pjob); out = getAllOutputArguments(pjob);

Display the random matrices.

celldisp(out);			
out{1} =			
0.9501	0.4860	0.4565	
0.2311	0.8913	0.0185	
0.6068	0.7621	0.8214	
out{2} =			
0.9501	0.4860	0.4565	
0.2311	0.8913	0.0185	
0.6068	0.7621	0.8214	
out{3} =			
0.9501	0.4860	0.4565	
0.2311	0.8913	0.0185	
0.6068	0.7621	0.8214	

Destroy the job.

destroy(pjob);

See Also

createJob, createTask, findJob, findResource, submit

createTask

Purpose	Create new task in job	
Syntax	obj = createTask(j, functionhandle, numoutputargs, inputargs) [, 'p1',v1,'p2',v2,) [, ' configuration' , 'ConfigurationName',)
Arguments	j	The job that the task object is created in.
	functionhandle	A handle to the function that is called when the task is evaluated.
	numoutputargs	The number of output arguments to be returned from execution of the task function.
	inputargs A row cell array specifying the input argument passed to the function functionhandle. Each e the cell array will be passed as a separate inpu argument.	
	p1, p2	Task object properties configured at object creation.
	v1, v2	Initial values for corresponding task object properties.
Description	 obj = createTask(j, functionhandle, numoutputargs, inputargs) creates a new task object in job j, and returns a reference, obj, to the added task object. obj = createTask(, 'p1',v1,'p2',v2,) adds a task object with the specified property values. If an invalid property name or property value is specified, the object will not be created. Note that the property value pairs can be in any format supported by the set function, i.e., param-value string pairs, structures, and param-value cell array pairs. If a structure is used, the structure field names are task object property names and the field values specify the property values. 	
	obj = createTask(, 'configuration', 'ConfigurationName',) creates a task job object with the property values specified in the configuration ConfigurationName. Configurations are defined in the file distcompUserConfig.m. For details about writing and applying configurations, see "Programming with User Configurations" on page 2-44.	

createTask

Example	<pre>Create a job object. jm = findResource('scheduler','type','jobmanager',</pre>		
	<pre>obj = createTask(j, @rand, 1, {10,10});</pre>		
	<pre>Run the job. submit(j); Get the output from the task evaluation. taskoutput = get(obj, 'OutputArguments');</pre>		
	Show the 10-by-10 random matrix.		
	<pre>disp(taskoutput{1});</pre>		
See Also	createJob		

dctconfig

Purpose	Configure settings for Distributed Computing Toolbox client session		
Syntax		dctconfig('p1', v1,) config = dctconfig('p1', v1,)	
Arguments	p1	Property to configure. Supported properties are 'port' and 'hostname'.	
	v1	Value for corresponding property.	
	config	Structure of configuration value.	
Description	dctconfig(' <i>p1</i> ', v value v1.	v1,) sets the client configuration property $p1$ with the	
	Note that the property value pairs can be in any format supported by the set function, i.e., param-value string pairs, structures, and param-value cell array pairs. If a structure is used, the structure field names are the property names and the field values specify the property values.		
	If the property is 'port', the specified value is used to set the port for the client session of the Distributed Computing Toolbox. This is useful in environments where the choice of ports is limited. By default, the client session uses a random port to communicate with the other sessions of the MATLAB Distributed Computing Engine. In networks where you are required to use specific ports, you use dctconfig to set the client's port.		
	for the client session the client computer should use is the ho computer. You can	nostname', the specified value is used to set the hostname n of the Distributed Computing Toolbox. This is useful when r is known by more than one hostname. The value you ostname by which the cluster nodes can contact the client find the default value by calling dctconfig without any efore any values have been set.	
		ig(p1', v1,) returns a structure to config. The field sure reflect the property names, while the field values are values.	

Example View the current settings for hostname and port.

Set the current client session port number to 21000 with hostname fdm4.

```
dctconfig('hostname', 'fdm4','port', 21000');
```

demote

Purpose	Demote job in job manager queue	
Syntax	demote(jm, job)	
Arguments	jmThe job manager object that contains the job.jobJob object to be demoted in the job queue.	
Description	demote(jm, job) demotes the job object job that is queued in the job manager jm.	
	If job is not the last job in the queue, demote exchanges the position of job and the job that follows it in the queue.	
See Also	createJob, findJob, promote, submit	

Purpose	Remove job or task object from its parent and from memory		
Syntax	destroy(obj)		
Arguments	obj	Job or task object deleted from memory.	
Description	destroy(obj) removes the job object reference or task object reference obj from the local session, and removes the object from the job manager memory. When obj is destroyed, it becomes an invalid object. You can remove an invalid object from the workspace with the clear command.		
	If multiple references to an object exist in the workspace, destroying one reference to that object invalidates all the remaining references to it. You should remove these remaining references from the workspace with the clear command.		
	•	ontained in a job will also be destroyed when a job object is eans that any references to those task objects will also be	
Remarks		s lost when you destroy an object, destroy should be used nas been retrieved from a job object.	
Example	Destroy a job and	its tasks.	
	<pre>jm = findResource('scheduler','type','jobmanager',</pre>		
	Note that task t is	also destroyed as part of job j.	
See Also	createJob, create	PTask	

dfeval

Purpose	Evaluate function using a cluster of computers	
Syntax	<pre>[y1,,ym] = dfeval(F, x1,,xn) [y1,,ym] = dfeval(F, x1,,xn, 'P1', V1, 'P2', V2,) [y1,,ym] = dfeval(F, x1,,xn, 'configuration', 'ConfigurationName',)</pre>	
Arguments	F	Function name, function handle, or cell array of function names or handles.
	x1,,xn	Cell arrays of input arguments to the functions.
	y1,,ym	Cell arrays of output arguments; each element of a cell array corresponds to each task of the job.
	' <i>P1</i> ', V1, ' <i>P2</i> ', V2,	Property name/property value pairs for the created job object; can be name/value pairs or structures.
Description	[y1,,ym] = df	$eval(F, x1, \ldots, xn)$ performs the equivalent of an feval

in a cluster of machines using the Distributed Computing Toolbox. dfeval evaluates the function F, with arguments provided in the cell arrays $x1, \ldots, xn$. F can be a function handle, a function name, or a cell array of function handles/function names where the length of the cell array is equal to the number of tasks to be executed. $x1, \ldots, xn$ are the inputs to the function F, specified as cell arrays in which the number of elements in the cell array equals the number of tasks to be executed. The first task evaluates function F using the first element of each cell array as input arguments; the second task uses the second element of each cell array, and so on. The sizes of $x1, \ldots, xn$ must all be the same.

The results are returned to $y1, \ldots, ym$, which are column-based cell arrays, each of whose elements corresponds to each task that was created. The number of cell arrays (m) is equal to the number of output arguments returned from each task. For example, if the job has 10 tasks that each generate three output arguments, the results of dfeval will be three cell arrays of 10 elements each.

 $y = dfeval(\dots, P1', V1, P2', V2, \dots)$ accepts additional arguments for configuring different properties associated with the job. Valid properties and property values are

- Job object property value pairs, specified as name/value pairs or structures. (Properties of other object types, such as scheduler, task, or worker objects are not permitted. Use a configuration to set scheduler and task properties.)
- 'JobManager', 'JobManagerName'. This specifies the job manager on which to run the job. If you do not use this property to specify a job manager, the default is to run the job on the first job manager returned by findResource.
- 'LookupURL', 'host:port'. This makes a unicast call to the job manager lookup service at the specified host and port. The job managers available for this job are those accessible from this lookup service. For more detail, see the description of this option on the findResource reference page.
- 'StopOnError', true | {false}. You may also set the value to logical 1 (true) or 0 (false). If true (1), any error that occurs during execution in the cluster will cause the job to stop executing. The default value is 0 (false), which means that any errors that occur will produce a warning but will not stop function execution.

```
[y1,...,ym] = dfeval(F, x1,...,xn, ...
```

'configuration', 'ConfigurationName',...) evaluates the function F in a cluster by using all the properties defined in the configuration ConfigurationName. The configuration settings are used to find and initialize a scheduler, create a job, and create tasks. Configurations are defined in the file distcompUserConfig.m. For details about writing and applying configurations, see "Programming with User Configurations" on page 2-44. Note that configurations enable you to use dfeval with any type of scheduler.

Example Create three tasks that return a 1-by-1, a 2-by-2, and a 3-by-3 random matrix.

```
y = dfeval(@rand,{1 2 3})
y =
       [ 0.9501]
       [2x2 double]
       [3x3 double]
```

Create two tasks that return random matrices of size 2-by-3 and 1-by-4.

```
y = dfeval(@rand,{2 1},{3 4});
y{1}
ans =
    0.8132  0.1389  0.1987
```

0	.0099	0.2028	0.6038	
y{2}				
ans =				
0	.6154	0.9218	0.1763	0.9355

Create two tasks, where the first task creates a 1-by-2 random array and the second task creates a 3-by-4 array of zeros.

```
y = dfeval({@rand @zeros}, {1 3}, {2 4});
y{1}
ans =
    0.0579
               0.3529
y{2}
ans =
     0
            0
                  0
                         0
     0
            0
                  0
                         0
     0
            0
                  0
                         0
```

Create five random 2-by-4 matrices using MyJobManager to execute tasks, where the tasks time out after 10 seconds, and the function will stop if an error occurs while any of the tasks are executing.

y = dfeval(@rand,{2 2 2 2 2},{4 4 4 4 4}, ... 'JobManager','MyJobManager','Timeout',10,'StopOnError',true);

See Also dfevalasync, feval, findResource

Purpose	Evaluate function asynchronously using a cluster of computers	
Syntax	Job = dfevalasync(F, numArgOut, x1,,xn, ' <i>P1</i> ', V1, ' <i>P2</i> ', V2,) Job = dfeval(F, numArgOut, x1,,xn, ' configuration ', 'ConfigurationName',)	
Arguments	Job	Job object created to evaluation the function.
	F	Function name, function handle, or cell array of function names or handles.
	numArgOut	Number of output arguments from each task's execution of function F.
	x1,,xn	Cell arrays of input arguments to the functions.
	' <i>P1</i> ', V1, ' <i>P2</i> ', V2,	Property name/property value pairs for the created job object; can be name/value pairs or structures.
Description	Job = dfevalasync(F, numArgOut, x1,,xn, 'P1', V1, 'P2', V2,) is equivalent to dfeval, except it returns immediately with a single output argument containing the job object that it has created and sent to the cluster.	
	<pre>'configuration', cluster by using al ConfigurationNam a scheduler, create file distcompUser(configurations, see</pre>	<pre>numArgOut, x1,,xn, , 'ConfigurationName',) evaluates the function F in a ll the properties defined in the configuration me. The configuration settings are used to find and initialize e a job, and create tasks. Configurations are defined in the Config.m. For details about writing and applying e "Programming with User Configurations" on page 2-44. rations enable you to use dfeval with any type of scheduler.</pre>
Example	Execute a sum function distributed in three tasks.	
	job = dfevalasync(@sum,1,{[1,2],[3,4],[5,6]}, 'jobmanager','MyJobManager');	
	When the job is fir	nished, you can obtain the results associated with the job.
	waitForState(job); data = getAllOutputArguments(job)	

data = [3] [7] [11]

data is an M-by-numArgOut cell array, where ${\tt M}$ is the number of tasks.

See Also dfeval, feval, getAllOutputArguments, waitForState

Purpose	Find job objects stored in scheduler	
Syntax	out = findJob(jm) [pending queued running finished] = findJob(jm) out = findJob(jm, 'p1', v1, 'p2', v2,)	
Arguments	jm pending queued running finished out p1,p2 v1,v2	Scheduler object in which to find the job. Array of jobs in scheduler jm whose State is pending. Array of jobs in scheduler jm whose State is queued. Array of jobs in scheduler jm whose State is running. Array of jobs in scheduler jm whose State is finished. Array of jobs found in scheduler jm. Job object properties to match. Values for corresponding object properties.
Description	<pre>scheduler jm. Job 'pending', 'queu are listed in the o [pending queue job objects stored in the order in wh to execute. out = findJob(; objects whose pro parameter-value Note that the pro function, i.e., par pairs. If a structure</pre>	jm) returns an array, out, of all job objects stored in the os in the array will be ordered by State in the following order: ued', 'running', 'finished'; within the 'queued' state, jobs order in which they are queued. d running finished] = findJob(jm) returns arrays of all lin the scheduler jm, by state. Jobs in the array queued will be nich they are queued, with the job at queued(1) being the next jm, 'p1', v1, 'p2', v2,) returns an array, out, of job operty names and property values match those passed as pairs, p1, v1, p2, v2. operty value pairs can be in any format supported by the set am-value string pairs, structures, and param-value cell array are is used, the structure field names are job object property eld values are the appropriate property values to match.

Jobs in the queued state are returned in the same order as they appear in the job queue service.

When a property value is specified, it must use the same exact value that the get function returns, including letter case. For example, if get returns the Name property value as MyJob, then findJob will not find that object while searching for a Name property value of myjob.

See Also createJob, findResource, findTask, submit

Purpose	Find available distributed computing resources	
Syntax	<pre>out = findResource('scheduler','type','SchedType') out = findResource('scheduler','type','jobmanager', 'LookupURL','host:port') out = findResource('scheduler','type','SchedType',, 'p1', v1,</pre>	
Arguments	out	Object or array of objects returned.
	'scheduler'	Literal string specifying that you are finding a scheduler, which can be a job manager or a third-party scheduler.
	'SchedType'	Specifies the type of scheduler: 'jobmanager', 'LSF', 'mpiexec', or any string that starts with 'generic'.
	'worker'	Literal string specifying that you are finding a worker.
	'LookupURL'	Literal string to indicate usage of a remote lookup service.
	'host:port'	Host (IP address or host name) and port of remote lookup service to use.
	p1, p2	Object properties to match.
	v1, v2	Values for corresponding object properties.
	'configuration'	Literal string to indicate usage of a configuration.
	'ConfigurationName'	Name of configuration to use, defined in distcompUserConfig.m.

Description

out = findResource('scheduler', 'type', 'SchedType')
out = findResource('worker') return an array, out, containing objects
representing all available distributed computing schedulers of the given type,
or workers. SchedType can be 'jobmanager', 'LSF', 'mpiexec', or any string
starting with 'generic'. You can use different scheduler types starting with
'generic' to identify one generic scheduler or configuration from another. For
third-party schedulers, job data is stored in the location specified by the
scheduler object's DataLocation property.

```
out = findResource('scheduler','type','jobmanager', ...
'LookupURL','host:port')
```

out = findResource('worker', 'LookupURL', 'host:port') use the lookup process of the job manager running at a specific location. The lookup process is part of a job manager. By default, findResource uses all the lookup processes that are available to the local machine via multicast. If you specify 'LookupURL' with a host and port, findResource uses the job manager lookup process running at that location. This URL is where the lookup is performed from, it is not necessarily the host running the job manager or worker. This unicast call is useful when you want to find resources that might not be available via multicast or in a network that does not support multicast. For more information about which ports these processes use, see "Setting TCP Ports" in the MATLAB Distributed Computing Engine System Administrator's Guide.

Note LookupURL is ignored when finding third-party schedulers.

out = findResource(..., p1', v1, p2', v2,...) returns an array, out, of resources whose property names and property values match those passed as parameter-value pairs, p1, v1, p2, v2.

Note that the property value pairs can be in any format supported by the set function.

When a property value is specified, it must use the same exact value that the get function returns, including letter case. For example, if get returns the Name property value as 'MyJobManager', then findResource will *not* find that object if searching for a Name property value of 'myjobmanager'.

	out = findResource('scheduler', 'configuration', 'ConfigurationName') returns an array, out, of schedulers whose property names and property values match those defined by the parameters in the configuration ConfigurationName. Configurations are defined in the file distcompUserConfig.m. For details about writing and applying configurations, see "Programming with User Configurations" on page 2-44.				
Remarks	Note that it is permissible to use parameter-value string pairs, structures, parameter-value cell array pairs, and configurations in the same call to findResource.				
Example	Find a particular job manager by its name and host.				
	jm1 = findResource('scheduler','type','jobmanager', 'Name', 'ClusterQueue1');				
	Find all job managers. In this example, there are four.				
	all_job_managers = findResource('scheduler','type','jobmanager') all_job_managers = distcomp.jobmanager: 1-by-4				
	Find all job managers accessible from the lookup service on a particular host.				
	jms = findResource('scheduler','type','jobmanager', 'LookupURL','123.123.1.1:6789');				
	Find a particular job manager accessible from the lookup service on a particular host. In this example, subnet2.host_alpha port 6789 is where the lookup is performed, but the job manager named SN2Jmgr might be running on another machine.				
	jm = findResource('scheduler','type','jobmanager', 'LookupURL', 'subnet2.host_alpha:6789', 'Name', 'SN2JMgr');				
	Find the LSF scheduler on the network.				
	lsf_sched = findResource('scheduler','type','LSF')				
See Also	findJob, findTask				

findTask

Purpose	Get task objects belonging to job object		
Syntax	<pre>tasks = findTask(obj) [pending running finished] = findTask(obj) tasks = findTask(obj, 'p1', v1, 'p2', v2,)</pre>		
Arguments	obj	Job object.	
	tasks	Returned task objects.	
	pending	Array of tasks in job obj whose State is pending.	
	running	Array of tasks in job obj whose State is running.	
	finished	Array of tasks in job obj whose State is finished.	
	p1, p2	Task object properties to match.	
	v1, v2	Values for corresponding object properties.	
Description	<pre>tasks = findTask(obj) gets a 1-by-N array of task objects belonging to object obj.</pre>		
	[pending running finished] = findTask(obj) returns arrays of all task objects stored in the job object obj, sorted by state.		
		(obj, $p1'$, v1, $p2'$, v2,) gets a 1-by-N array of ing to a job object obj. The returned task objects will be only pecified property-value pairs.	
	Note that the property value pairs can be in any format supported by the set function, i.e., param-value string pairs, structures, and param-value cell array pairs. If a structure is used, the structure field names are object property names and the field values are the appropriate property values to match.		
	When a property value is specified, it must use the same exact value that the get function returns, including letter case. For example, if get returns the Name property value as MyTask, then findTask will not find that object while searching for a Name property value of mytask.		

Remarks	If obj is contained in a remote service, findTask will result in a call to the remote service. This could result in findTask taking a long time to complete, depending on the number of tasks retrieved and the network speed. Also, if the remote service is no longer available, an error will be thrown.
Example	Create a job object.
	jm = findResource('scheduler','type','jobmanager', 'name','MyJobManager','LookupURL','JobMgrHost'); obj = createJob(jm);
	Add a task to the job object.
	createTask(obj, @rand, 1, {10})
	Create the task object t, which refers to the task we just added to obj.
	t = findTask(obj)
See Also	createJob, createTask, findJob

Purpose	Return object prope	orties
Syntax	get(obj) out = get(obj) out = get(obj,' <i>Pr</i>	ropertyName')
Arguments	obj	An object or an array of objects.
	'PropertyName'	A property name or a cell array of property names.
	out	A single property value, a structure of property values, or a cell array of property values.
Description	get(obj) returns al line for obj.	ll property names and their current values to the command
		turns the structure out where each field name is the name , and each field contains the value of that property.
	specified by <i>Proper</i> n-by-1 cell array of 1-by-n cell array of an m-by-n cell array	ropertyName') returns the value out of the property tyName for obj. If <i>PropertyName</i> is replaced by a 1-by-n or strings containing property names, then get returns a values to out. If obj is an array of objects, then out will be y of property values where m is equal to the length of obj e number of properties specified.
Remarks	you can make use o	property name, you can do so without regard to case, and f property name completion. For example, if jm is a job n these commands are all valid and return the same result.
	out = get(jm,' out = get(jm,' out = get(jm,'	hostaddress');

Example This example illustrates some of the ways you can use get to return property values for the job object j 1.

```
get(j1,'State')
                     ans =
                     pending
                     get(j1,'Name')
                     ans =
                     MyJobManager_job
                     out = get(j1);
                     out.State
                     ans =
                     pending
                     out.Name
                     ans =
                     MyJobManager_job
                     two_props = {'State' 'Name'};
                     get(j1, two_props)
                     ans =
                          'pending'
                                       'MyJobManager_job'
See Also
                   inspect, set
```

getAllOutputArguments

Purpose	Retrieve output arguments from evaluation of all tasks in job object		
Syntax	<pre>data = getAllOutputArguments(obj)</pre>		
Arguments	obj data	Job object whose tasks generate output arguments. M-by-N cell array of job results.	
Description	contained in the ta M-by-N cell array task in the job. Ea output arguments arrays containing N output argumen	tputArguments(obj) returns data, the output data asks of a finished job. If the job has M tasks, each row of the data contains the output arguments for the corresponding ach row has N columns, where N is the greatest number of a from any one task in the job. The N elements of a row are the output arguments from that task. If a task has less than hts, the excess arrays in the row for that task are empty. The in data will be the same as the order of the tasks contained	
Remarks	remote service, wh amount of data be	job manager, getAllOutputArguments results in a call to a hich could take a long time to complete, depending on the sing retrieved and the network speed. Also, if the remote er available, an error will be thrown.	
	data from the loca	a call to getAllOutputArguments will not remove the output ation where it is stored. To remove the output data, use the to remove the individual task or their parent job object.	
		tion returned by getAllOutputArguments can be obtained by outArguments property of each task in the job.	
Example	jm = findReso 'na j = createJob t = createTas submit(j);	nerate a random matrix. purce('scheduler','type','jobmanager', me','MyJobManager','LookupURL','JobMgrHost'); o(jm, 'Name', 'myjob'); sk(j, @rand, 1, {10}); OutputArguments(j);	

Display the 10-by-10 random matrix.

disp(data{1});
destroy(j);

See Also

submit

getCurrentJob

Purpose	Get job object whose task is currently being evaluated	
Syntax	job = getCurrent	Job
Arguments	job	The job object that contains the task currently being evaluated by the worker session.
Description	job = getCurrentJob returns the job object that is the Parent of the task currently being evaluated by the worker session.	
Remarks	If the function is executed in a MATLAB session that is not a worker, you get an empty result.	
See Also	getCurrentJobmanager, getCurrentTask, getCurrentWorker	

Purpose	Get job manager object that distributed sent current task	
Syntax	jm = getCurrentJ	obmanager
Arguments	jm	The job manager object that distributed the task currently being evaluated by the worker session.
Description		obmanager returns the job manager object that has sent the ag evaluated by the worker session. jm is the Parent of the
Remarks	If the function is ea an empty result.	xecuted in a MATLAB session that is not a worker, you get
	•	istributed by a third-party scheduler instead of a job entJobmanager returns a distcomp.taskrunner object.
See Also	getCurrentJob,ge	tCurrentTask,getCurrentWorker

getCurrentTask

Purpose	Get task object currently being evaluated in this worker session	
Syntax	task = getCurrentTask	
Arguments	task The task object that the worker session is currently evaluating.	
Description	task = getCurrentTask returns the task object that is currently being evaluated by the worker session.	
Remarks	If the function is executed in a MATLAB session that is not a worker, you get an empty result.	
See Also	getCurrentJob, getCurrentJobmanager, getCurrentWorker	

Purpose	Get worker object currently running this session
Syntax	worker = getCurrentWorker
Arguments	worker The worker object that is currently evaluating the task that contains this function.
Description	worker = getCurrentWorker returns the worker object representing the session that is currently evaluating the task that calls this function.
Remarks	If the function is executed in a MATLAB session that is not a worker or if you are using a third-party scheduler instead of a job manager, you get an empty result.
Example	Create a job with one task, and have the task return the name of the worker that evaluates it.
	<pre>jm = findResource('scheduler','type','jobmanager',</pre>
	The function of the task t is an anonymous function that first executes getCurrentWorker to get an object representing the worker that is evaluating the task. Then the task function uses get to examine the Name property value of that object. The result is placed in the OutputArgument property of the task.
See Also	getCurrentJob, getCurrentJobmanager, getCurrentTask

getDebugLog

Purpose	Return output messages from parallel job run by mpiexec scheduler		
Syntax	str = getDebug	gLog (mpiexec, pjob)	
Arguments	str	str Variable to which messages are returned as a string expression.	
	mpiexec	Scheduler object referring to mpiexec scheduler, created by findResource.	
	pjob	Object identifying parallel job whose messages you want.	
Description	getDebugLog (mpiexec, job) returns any output written to the standard output or standard error stream by the job identified by pjob, being run by the scheduler identified by mpiexec.		
See Also	findResource,	findResource, createParallelJob	

Purpose	Perform global	operation across all labs
Syntax	gop(@F, x)	
Arguments	F	Function to operate across labs.
	x	Argument to function F, should be same variable on all labs.
Description		the reduction via the function F of the quantities x from each lab. uplicated on all labs.
		(x,y) should accept two arguments of the same type and sult of that type, so it can be used iteratively, that is,
	F(F(x1,x2	2),F(x3,x4))
	The function F	should be associative, that is,
	F(F(x1, x2), $x3) = F(x1, F(x2, x3))$
Example	Calculate the s	um of all labs' value for x.
	gop(@plus,	x)
	Find the maxir	num value of x among all the labs.
	gop(@max,x)
	Perform the ho	rizontal concatenation of x from all labs.
	gop(@horzc	at,x)
	Calculate the 2	-norm of x from all labs.
	gop(@(a1,a	2)norm([a1 a2]),x)
See Also	labBarrier, nu	ımlabs

help

Purpose	Display help for toolbox functions in Command Window	
Syntax	help <i>class/fu</i>	nction
Arguments	class	A Distributed Computing Toolbox object class: distcomp.jobmanager, distcomp.job, or distcomp.task.
	function	A function for the specified class. To see what functions are available for a class, see the methods reference page.
Description	help <i>class/fu</i> the given class.	nction returns command-line help for the specified function of
	•	now the class for the function, use class(obj), where <i>function</i> class as the object obj.
Example	Get help on fun classes.	actions from each of the Distributed Computing Toolbox object
	help distco	omp.jobmanager/createJob
	•	omp.job/cancel
	help distco	omp.task/waitForState
	class(j1)	
	ans =	
	distcomp.jo	
	help distco	omp.job/createTask
See Also	methods	

inspect

Purpose	Open the Property Inspector		
Syntax	inspect(obj)		
Arguments	obj An object or an array of objects.		
Description	inspect(obj) opens the Property Inspector and allows you to inspect and set properties for the object obj.		
Remarks	You can also open the Property Inspector via the Workspace browser by double-clicking an object.		
	The Property Inspector does not automatically update its display. To refresh the Property Inspector, open it again.		
	Note that properties that are arrays of objects are expandable. In the figure of the example below, the Tasks property is expanded to enumerate the individual task objects that make up this property. These individual task objects can also be expanded to display their own properties.		
Example	Open the Property Inspector for the job object j1.		

inspect(j1)

Property Inspector	
📦 dml.job	
- CreateTime	Tue Sep 28 11:27:35 EDT : 🔺
 FileDependencies 	E
— FinishTime	
— ID	4
— JobData	🖽 [0x0 double array]
— MaximumNumberOfWorkers	6
— MinimumNumberOfWorkers	1
— Name	job_PT109
— RestartWorker	🐺 True
— StartTime	
- State	pending
— SubmitTime	
— Tag	
🖵 Tasks	
±-1	
±-2	
l i⊨ 3	•

See Also

get, set

jobStartup

Purpose	Job startup M-file for user-defined options		
Syntax	jobStartup(job)		
Arguments	job	The job for which this startup is being executed.	
Description	jobStartup(job) runs automatically on a worker the first time the worker evaluates a task for a particular job. You do not call this function from the client session, nor explicitly as part of a task function.		
	The function M-file	e resides in the worker's MATLAB installation at	
	MATLABROOT/toolbox/distcomp/user/jobStartup.m		
		the file to define job initialization actions to be performed on t first evaluates a task for this job.	
	of the job's FileDe	can create a file called jobStartup.m and include it as part pendencies property. The version of the file in takes precedence over the version in the worker's MATLAB	
	For further detail,	see the text in the installed jobStartup.m file.	
See Also	Functions taskFinish, taskS	Startup	
	Properties		

FileDependencies

Purpose	Block execution until all labs have reached this call
Syntax	labBarrier
Description	labBarrier blocks execution of a parallel algorithm until all labs have reached the call to labBarrier. This is useful for coordinating access to shared resources such as file I/O.
Example	<pre>In this example, all labs know the shared data filename. fname = 'c:\data\datafile.mat';</pre>
	Lab 1 writes some data to the file, which all other labs will read.
	<pre>if labindex == 1 data = randn(100, 1); save(fname, 'data'); pause(5) %allow time for file to become available to other labs end</pre>
	All labs wait until all have reached the barrier; this ensures that no lab attempts to load the file until lab 1 writes to it.
	labBarrier; load(fname);
See Also	labBroadcast

labBroadcast

Purpose	Send data to all labs or receive data sent to all labs	
Syntax	shared_data = labBroadcast(senderlab, data) shared_data = labBroadcast(senderlab)	
Arguments	senderlabThe labindex of the lab sending the broadcast.dataThe data being broadcast. This argument is required only for the lab that is broadcasting. The absence of this argument indicates that a lab is receiving.	
	shared_data The broadcast data as it is received on all other labs.	
Description	<pre>shared_data = labBroadcast(senderlab, data) sends the specified data to all executing labs. The data is broadcast from the lab with labindex == senderlab, and received by all other labs.</pre>	
	<pre>shared_data = labBroadcast(senderlab) receives on each executing lab the specified shared_data that was sent from the lab whose labindex is senderlab.</pre>	
	If labindex is not senderlab, then you do not include the data argument. This indicates that the function is to receive data, not broadcast it. The received data, shared_data, is identical on all labs.	
	This function blocks execution until the lab's involvement in the collective broadcast operation is complete. Because some labs may complete their call to labBroadcast before others have started, use labBarrier to guarantee that all labs are at the same point in a program.	
Example	<pre>In this case, the broadcaster is the lab whose labindex is 1. broadcast_id = 1; if labindex == broadcast_id data = randn(10); shared_data = labBroadcast(broadcast_id, data); else shared_data = labBroadcast(broadcast_id); end</pre>	

See Also labBarrier, labindex

labindex

Purpose	Return index of this lab
Syntax	id = labindex
Description	id = labindex returns the index of the lab currently executing the function. labindex is assigned to each lab when a job begins execution, and applies only for the duration of that job. The value of labindex spans from 1 to n, where n is the number of labs running the current job, defined by numlabs.
See Also	numlabs

Purpose	Test to see if messages	are ready to be received from other lab
Syntax	is_data_available =	
Arguments	source	labindex of a particular lab from which to test for message.
	tag	Tag defined by the sending lab's labSend function to identify particular data.
	'any'	String to indicate that all labs should be tested for a message.
	is_data_available	Boolean indicating if message is ready to be received.
Description		labProbe returns a logical value indicating whether r this lab to receive with the labReceive function.
	is_data_available = specified lab.	labProbe(source) tests for a message only from the
	is_data_available = the specified tag, from a	<pre>labProbe('any', tag) tests only for a message with any lab.</pre>
	is_data_available = specified lab and tag.	labProbe(source, tag) tests for a message from the
		source, tag] = labProbe returns labindex and tag o data is available, source and tag are returned as [].
See Also	labindex, labReceive,	labSend

labReceive

Purpose	Receive data from anoth	er lab
Syntax	data = labReceive data = labReceive(sou data = labReceive(' a r data = labReceive(sou [data, source, tag] =	ny', tag) urce, tag)
Arguments	source	labindex of a particular lab from which to receive data.
	tag	Tag defined by the sending lab's labSend function to identify particular data.
	'any'	String to indicate that data can come from any lab.
	data	Data sent by sending lab's labSend function.
Description	data = labReceive rece	eives data from any lab with any tag.
	data = labReceive(sou	arce) receives data from the specified lab with any tag
	data = labReceive(' a r specified tag.	y', tag) receives data from any lab with the
	data = labReceive(sou with the specified tag.	urce, tag) receives data from only the specified lab
	[data, source, tag] = data.	alabReceive returns the source and tag with the
Remarks	This function blocks exe labSend occurs in the se	cution in the lab until the corresponding call to nding lab.
See Also	labBarrier, labindex,]	LabProbe, labSend

Purpose	Send data to another specified lab	
Syntax	labSend(data, destination) labSend(data, destination, tag)	
Arguments	dataData sent to the other lab; any MATLAB data type.destinationlabindex of receiving lab.tagNonnegative integer to identify data.	
Description	<pre>labSend(data, destination) sends the data to the specified destination, with a tag of 0. labSend(data, destination, tag) sends the data to the specified destination with the specified tag. data can be any MATLAB data type. destination identifies the labindex of the receiving lab, and must be either a scalar or a vector of integers between 1 and numlabs; it cannot be labindex (i.e., the current lab). tag can be any nonnegative integer.</pre>	
Remarks	This function might return before the corresponding labReceive completes in the receiving lab.	
See Also	labBarrier, labindex, labProbe, labReceive, numlabs	

length

Purpose	Return length of object array	
Syntax	length(obj)	
Arguments	obj An object or an array of objects.	
Description	<pre>length(obj) returns the length of obj. It is equivalent to the comman max(size(obj)).</pre>	ıd
Example	Examine how many tasks are in the job j1.	
	length(j1.Tasks) ans = 9	
See Also	size	

methods

Purpose	List functions o	of object class	
Syntax	methods(obj) out = methods(obj)		
Arguments	obj	An object or an array of objects.	
	out	Cell array of strings.	
Description	methods(obj) returns the names of all methods for the class of which obj is an instance.		
	out = methods strings.	(Obj) returns the names of the methods	as a cell array of
Example	Create job man available for ea	ager, job, and task objects, and examine ch.	what methods are
	jm = findResource('scheduler','type','jobmanager', 'name','MyJobManager','LookupURL','JobMgrHost'); methods(jm) Methods for class distcomp.jobmanager: createJob findJob pause resume		
	j1 = create methods(j1) Methods for		
	cancel	destroy	promote
	createTask	findTask	submit
	demote	getAllOutputArguments	waitForState
	methods(t1) Methods for	<pre>r class distcomp.task:</pre>	
	cancel de	estroy waitForState	
See Also	help		

mpiLibConf

Purpose	Return location of MPI implementation
Syntax	[primaryLib, extras] = mpiLibConf
Arguments	primaryLib
	extras
Description	[primaryLib, extras] = mpiLibConf returns the MPI implementation library to be used by a parallel job. primaryLib is the name of the shared library file containing the MPI entry points. extras is a cell array of other library names required by the MPI library.
	To supply an alternative MPI implementation, create an M-file called mpiLibConf, and place it on the MATLAB path. The recommended location is \$MATLAB/toolbox/distcomp/user.
Remarks	Under all circumstances, the MPI library must support all MPI-1 functions. Additionally, the MPI library must support null arguments to MPI_Init as defined in section 4.2 of the MPI-2 standard. The library must also use an mpi.h header file that is fully compatible with MPICH2.
	When used with the MathWorks job manager, the MPI library must support the following additional MPI-2 functions:
	 MPI_Open_port MPI_Comm_accept MPI_Comm_connect
Example	View the current MPI implementation library. mpiLibConf mpich2.dll

Purpose	Set options for MPI communication
Syntax	<pre>mpiSettings('DeadlockDetection', 'on') mpiSettings('MessageLogging', 'on') mpiSettings('MessageLoggingDestination', 'CommandWindow') mpiSettings('MessageLoggingDestination', 'stdout') mpiSettings('MessageLoggingDestination', 'File', <fname>)</fname></pre>
Description	<pre>mpiSettings('DeadlockDetection', 'on') turns on deadlock detection during calls to labSend and labReceive (the default is 'off' for performance reasons). If deadlock is detected, a call to labReceive might cause an error. Although it is not necessary to enable deadlock detection on all labs, this is the most useful option.</pre>
	mpiSettings('MessageLogging','on') turns on MPI message logging. The default is 'off'. The default destination is the MATLAB command window.
	mpiSettings('MessageLoggingDestination','CommandWindow') sends MPI logging information to the MATLAB command window. If the task within a parallel job is set to capture command window output, the MPI logging information will be present in the task's CommandWindowOutput property.
	mpiSettings('MessageLoggingDestination','stdout') sends MPI logging information to the standard output for the MATLAB process. If you are using a job manager, this is the MDCE service log file; if you are using an mpiexec scheduler, this is the mpiexec debug log, which you can read with getDebugLog.
	mpiSettings('MessageLoggingDestination','File', <fname>) sends MPI logging information to the specified file.</fname>
Remarks	Setting the MessageLoggingDestination does not automatically enable message logging. A separate call is required to enable message logging.
	mpiSettings has to be called on the lab, not the client. That is, it should be called within the task function, within jobStartup.m or within taskStartup.m.

mpiSettings

Example % in "jobStartup.m" for a parallel job
mpiSettings('DeadlockDetection', 'on');
myLogFname = sprintf('%s_%d.log', tempname, labindex);
mpiSettings('MessageLoggingDestination', 'File', myLogFname);
mpiSettings('MessageLogging', 'on');

Purpose	Return total number of labs operating in parallel on current job
Syntax	n = numlabs
Description	n = numlabs returns the total number of labs currently operating on the current job. This value is the maximum value that can be used with labSend and labReceive.
See Also	labindex, labReceive, labSend

pause

Purpose	Pause job manager queue	
Syntax	pause(jm)	
Arguments	jm	Job manager object whose queue is paused.
Description	pause(jm) pauses the job manager's queue so that jobs waiting in the queued state will not run. Jobs that are already running also pause, after completion of tasks that are already running. No further jobs or tasks will run until the resume function is called for the job manager.	
	The pause function	on does nothing if the job manager is already paused.
See Also	resume, waitFor	State

promote

Purpose	Promote job in j	Promote job in job manager queue	
Syntax	promote(jm, jo	promote(jm, job)	
Arguments	jm	The job manager object that contains the job.	
	job	Job object promoted in the queue.	
Description	promote(job) p jm.	promote(job) promotes the job object job, that is queued in the job manager jm.	
	If the job object is not the first job in the queue, the position of job and the previous job object are exchanged.		
See Also	createJob, demote, findJob, submit		

resume

Purpose	Resume processing queue in job manager	
Syntax	resume(jm)	
Arguments	jm Job manager object whose queue is resumed.	
Description	resume(jm) resumes processing of the job manager's queue so that jobs waiting in the queued state will be run. This call will do nothing if the job manager is not paused.	
See Also	pause, waitForState	

Purpose	Configure or display object properties		
Syntax	<pre>set(obj) props = set(obj) set(obj,'PropertyName props = set(obj,'PropertyName set(obj,'PropertyName set(obj,'configuration set(obj,PN,PV) set(obj,S)</pre>	ertyName')	
Arguments	obj	An object or an array of objects.	
	'PropertyName'	A property name for obj.	
	PropertyValue	A property value supported by <i>PropertyName</i> .	
	PN	A cell array of property names.	
	PV	A cell array of property values.	
	props	A structure array whose field names are the property names for obj.	
	S	A structure with property names and property values.	
	'configuration'	Literal string to indicate usage of a configuration.	
	'ConfigurationName'	Name of configuration to use, defined in distcompUserConfig.m.	
Description	<pre>set(obj) displays all configurable properties for obj. If a property has a finite list of possible string values, these values are also displayed.</pre>		
	possible values to the str property names of obj, ar	ns all configurable properties for obj and their ucture props. The field names of props are the nd the field values are cell arrays of possible property not have a finite set of possible values, its cell array	

is empty.

	<pre>set(obj,'PropertyName') displays the valid values for PropertyName if it possesses a finite list of string values.</pre>
	<pre>props = set(obj,'PropertyName') returns the valid values for PropertyName to props. props is a cell array of possible string values or an empty cell array if PropertyName does not have a finite list of possible values.</pre>
	<pre>set(obj,'PropertyName',PropertyValue,) configures one or more property values with a single command.</pre>
	<pre>set(obj,PN,PV) configures the properties specified in the cell array of strings PN to the corresponding values in the cell array PV. PN must be a vector. PV can be m-by-n, where m is equal to the number of objects in obj and n is equal to the length of PN.</pre>
	<pre>set(obj,S) configures the named properties to the specified values for obj. S is a structure whose field names are object properties, and whose field values are the values for the corresponding properties.</pre>
	<pre>set(obj,'configuration', 'ConfigurationName',) sets the object properties with values specified in the configuration ConfigurationName. Configurations are defined in the file distcompUserConfig.m. For details about writing and applying configurations, see "Programming with User Configurations" on page 2-44.</pre>
Remarks	You can use any combination of property name/property value pairs, structure arrays, and cell arrays in one call to set. Additionally, you can specify a property name without regard to case, and you can make use of property name completion. For example, if j1 is a job object, the following commands are all valid and have the same result.
	set(j1,'Timeout',20) set(j1,'timeout',20) set(j1,'timeo',20)
Examples	This example illustrates some of the ways you can use set to configure property values for the job object j1.
	<pre>set(j1,'Name','Job_PT109','Timeout',60);</pre>

```
props1 = {'Name' 'Timeout'};
values1 = {'Job_PT109' 60};
set(j1, props1, values1);
S.Name = 'Job_PT109';
S.Timeout = 60;
set(j1,S);
```

See Also

get, inspect

size

Purpose	Return size of object array	
Syntax	<pre>d = size(obj) [m,n] = size(obj) [m1,m2,,mn] = size(obj) m = size(obj,dim)</pre>	
Arguments	obj	An object or an array of objects.
	dim	The dimension of obj.
	d	The number of rows and columns in obj.
	m	The number of rows in obj, or the length of the dimension specified by dim.
	n	The number of columns in obj.
	m1,m2,, mn	The lengths of the first n dimensions of obj.
Description	d = size(obj) returns the two-element row vector d containing the number of rows and columns in obj.	
	[m,n] = size(obj) returns the number of rows and columns in separate output variables.	
	<pre>[m1,m2,m3,,mn] = size(obj) returns the length of the first n dimensions of obj.</pre>	
	<pre>m = size(obj,dim) returns the length of the dimension specified by the scal dim. For example, size(obj,1) returns the number of rows.</pre>	
See Also	length	

submit

Purpose	Queue job in job queue service		
Syntax	<pre>submit(obj)</pre>		
Arguments	obj	Job object to be queued.	
Description		s the job object, obj, in the scheduler queue. The scheduler s determined when the job was created.	
Remarks	When a job contained in a scheduler is submitted, the job's State property is set to queued, and the job is added to the list of jobs waiting to be executed. The jobs in the waiting list are executed in a first in, first out manner; that is, the order in which they were submitted, except when the sequence is altered by promote, demote, cancel, or destroy.		
Example	Find the job manager named jobmanager1 using the lookup service on host JobMgrHost.		
		urce('scheduler','type','jobmanager', e','jobmanager1','LookupURL','JobMgrHost');	
	j1 = createJob(jm1);		
	Add a task object to be evaluated for the job.		
	<pre>t1 = createTask(j1, @myfunction, 1, {10, 10});</pre>		
	Queue the job objec submit(j1);	t in the job manager.	
See Also	createJob, findJob		

taskFinish

Purpose	Task finish M-file for user-defined options		
Syntax	taskFinish(task)		
Arguments	task	The task being evaluated by the worker.	
Description	taskFinish(task) runs automatically on a worker each time the worker finishes evaluating a task for a particular job. You do not call this function from the client session, nor explicitly as part of a task function.		
	The function M-file resides in the worker's MATLAB installation at		
	MATLABROOT/toolbox/distcomp/user/taskFinish.m		
	You add M-code to the file to define task finalization actions to be performed on the worker every time it finishes evaluating a task for this job.		
	Alternatively, you can create a file called taskFinish.m and include it as part of the job's FileDependencies property. The version of the file in FileDependencies takes precedence over the version in the worker's MATLAB installation.		
	For further detail, see the text in the installed taskFinish.m file.		
See Also	Functions jobStartup, taskStartup		
	Properties		

FileDependencies

Purpose	Task startup M-file for user-defined options			
Syntax	taskStartup(task)			
Arguments	task The task being evaluated by the worker.			
Description	taskStartup(task) runs automatically on a worker each time the worker evaluates a task for a particular job. You do not call this function from the client session, nor explicitly as part of a task function.			
	The function M-file resides in the worker's MATLAB installation at			
	MATLABROOT/toolbox/distcomp/user/taskStartup.m			
	You add M-code to the file to define task initialization actions to be performed on the worker every time it evaluates a task for this job.			
	Alternatively, you can create a file called taskStartup.m and include it as part of the job's FileDependencies property. The version of the file in FileDependencies takes precedence over the version in the worker's MATLAB installation.			
	For further detail, see the text in the installed taskStartup.m file.			
See Also	ee Also Functions jobStartup, taskFinish Properties FileDependencies			

waitForState

Purpose	Wait for object to change state		
Syntax	waitForState(obj) waitForState(obj, ' <i>state</i> ') waitForState(obj, ' <i>state</i> ', timeout)		
Arguments	obj	Job or task object whose change in state to wait for.	
	'state'	Value of the object's State property to wait for.	
	timeout	Maximum time to wait, in seconds.	
Description	waitForState(obj) blocks execution in the client session until the job or task identified by the object obj reaches the 'finished' state or fails. For a job object, this occurs when all its tasks are finished processing on remote workers.		
	waitForState(obj, 'state') blocks execution in the client session until the specified object changes state to the value of 'state'. For a job object, the valid states to wait for are 'queued', 'running', and 'finished'. For a task object, the valid states are 'running' and 'finished'.		
	If the object is currently or has already been in the specified state, a wait is not performed and execution returns immediately. For example, if you execute waitForState(job, 'queued') for job already in the 'finished' state, the call returns immediately.		
	<pre>waitForState(obj, 'state', timeout) blocks execution until either the object reaches the specified 'state', or timeout seconds elapse, whichever happens first.</pre>		
Example	Submit a job to the queue, and wait for it to finish running before retrieving its results.		
		(job, 'finished') tAllOutputArguments(job)	
See Also	pause, resume		

4

Property Reference

This chapter describes the Distributed Computing Toolbox object properties in detail.

Properties — CategoricalContains a series of tables that group properties by categoryList (p. 4-2)Properties — AlphabeticalLists all the properties alphabeticallyList (p. 4-7)Lists all the properties alphabetically

Properties – Categorical List

This section contains descriptions of the toolbox properties.

Job Manager Properties	Properties of job manager objects
Scheduler Properties	Properties of scheduler objects
Job Properties	Properties of job objects
Task Properties	Properties of task objects
Worker Properties	Properties of worker objects

Job Manager Properties

• 1	
BusyWorkers	Indicate workers currently running tasks
Configuration	Specify configuration to apply to object or toolbox function
HostAddress	Indicate IP address of host machine running job manager
HostName	Indicate name of host machine running job manager
IdleWorkers	Indicate which workers are idle and available to run tasks
Jobs	Indicate jobs contained in job manager
Name	Indicate name of job manager
NumberOfBusyWorkers	Indicate number of workers currently running tasks
NumberOfIdleWorkers	Indicate number of workers available to run tasks
State	Indicate current state of job manager

Scheduler Properties

ClusterMatlabRoot	Specify MATLAB root for cluster
ClusterName	Indicate name of LSF cluster
Configuration	Specify configuration to apply to object or toolbox function
DataLocation	Specify directory where job data is stored
EnvironmentSetMethod	Specify means of setting environment variables for mpiexec scheduler
HasSharedFilesystem	Specify whether nodes are to share DataLocation
Jobs	Indicate jobs contained in directory identified by DataLocation property value
MasterName	Indicate name of LSF master node
MatlabCommandToRun	Indicate MATLAB command for generic scheduler to run
MpiexecFileName	Specify pathname of executable mpiexec command
SubmitArguments	Specify additional arguments to use when submitting job to LSF or mpiexec scheduler
SubmitFcn	Specify function to run when job submitted to generic scheduler
Туре	Indicate type of generic scheduler
WorkerMachineOsType	Specify operating system of nodes on which mpiexec scheduler will start labs
Job Properties	

Configuration	Specify configuration to apply to object or toolbox function
CreateTime	Indicate when job was created

FileDependencies	Indicate directories and files that worker can access
FinishedFcn	Specify callback to execute when job finishes running
FinishTime	Indicate when job finished
ID	Indicate object identifier
JobData	Indicate data made available to all workers for job's tasks
MaximumNumberOfWorkers	Specify maximum number of workers to perform tasks of a job
MinimumNumberOfWorkers	Specify minimum number of workers to perform tasks of a job
Name	Specify name for job object
Parent	Indicate parent job manager object of job
PathDependencies	Specify directories to add to MATLAB worker path
QueuedFcn	Specify M-file function to execute when job is added to queue
RestartWorker	Specify whether to restart MATLAB on worker before it evaluates task
RunningFcn	Specify M-file function to execute when job or task starts running
StartTime	Indicate when job started running
State	Indicate current state of job object
SubmitTime	Indicate when job was submitted to job queue
Тад	Specify label to associate with job object
Tasks	Indicate tasks contained in job object
Timeout	Specify time limit for completion of job
Туре	Indicate type of object

UserData	Specify data to associate with job object $% \left({{{\left({{{{\left({{{}_{{\rm{s}}}} \right)}}} \right)}_{\rm{s}}}}} \right)$
UserName	Indicate user who created job

Task Properties

CaptureCommandWindowOutput	Specify whether to return command window output
CommandWindowOutput	Indicate text produced by execution of task object's function
Configuration	Specify configuration to apply to object or toolbox function
CreateTime	Indicate when task was created
ErrorIdentifier	Indicate task error identifier
ErrorMessage	Indicate output message from task error
FinishedFcn	Specify callback to execute when task finishes running
FinishTime	Indicate when task finished
Function	Indicate function called when evaluating task
ID	Indicate object identifier
InputArguments	Indicate input arguments to task object
NumberOfOutputArguments	Indicate number of arguments returned by task function
OutputArguments	Data returned from the execution of task
Parent	Indicate parent job object of task
RunningFcn	Specify M-file function to execute when job or task starts running
State	Indicate current state of task object
StartTime	Indicate when task started running
Timeout	Specify time limit for completion of task

Туре	Indicate type of object
UserData	Specify data to associate with task object
Worker	Indicate worker session that performed task

Worker Properties

CurrentJob	Indicate job whose task the worker is currently running
CurrentTask	Indicate task that worker is currently running
HostAddress	Indicate IP address of host machine running worker session
HostName	Indicate name of host machine running worker session
Name	Indicate name of worker object
PreviousJob	Indicate job whose task the worker previously ran
PreviousTask	Indicate task that worker previously ran
State	Indicate current state of worker object

Properties – Alphabetical List

This section contains detailed descriptions of the Distributed Computing Toolbox object properties. Each property reference page contains some or all of the following information:

- The property name
- A description of the property
- The property characteristics, including
 - Usage the object(s) the property is associated with
 - Read-only the condition under which the property is read-only
 A property can be read-only always, never, or depending on the state of the

object. You can configure a property value using the set command or dot notation. You can return the current property value using the get command or dot notation.

- Data type — the property data type

This is the data type you use when specifying a property value

• Valid property values including the default value

When property values are given by a predefined list, the default value is usually indicated by {} (curly braces).

- An example using the property
- Related properties and functions

BusyWorkers

Purpose	Indicate workers currently running tasks		
Description	The BusyWorkers property value indicates which workers are currently running tasks for the job manager.		
Characteristics	Usage	Job manager object	
	Read-only	Always	
	Data type	Array of worker objects	
Values	As workers complete tasks and assume new ones, the lists of workers in BusyWorkers and IdleWorkers can change rapidly. If you examine these two properties at different times, you might see the same worker on both lists if that worker has changed its status between those times. If a worker stops unexpectedly, the job manager's knowledge of that as a busy or idle worker does not get updated until the job manager runs the next job and tries to send a task to that worker.		
Example	Examine the workers currently running tasks for a particular job manager.		
	-	esource('scheduler','type','jobmanager', name','MyJobManager','LookupURL','JobMgrHost'); ning_tasks = get(jm, 'BusyWorkers')	
See Also	,	aximumNumberOfWorkers,MinimumNumberOfWorkers, orkers,NumberOfIdleWorkers	

Purpose	Specify whether to return command window output	
Description	CaptureCommandWindowOutput specifies whether to return command window output for the evaluation of a task object's Function property.	
	If CaptureCommandWindowOutput is set true (or logical 1), the command window output will be stored in the CommandWindowOutput property of the task object. If the value is set false (or logical 0), the task does not retain command window output.	
Characteristics	Usage	Task object
	Read-only	While task is running or finished
	Data type	Logical
Values	The value of CaptureCommandWindowOutput can be set to true (or logical 1) or false (or logical 0). When you perform get on the property, the value returned is logical 1 or logical 0. The default value is logical 0 to save network bandwidth in situations where the output is not needed.	
Example	Set all tasks in a job to retain any command window output generated during task evaluation.	
	<pre>jm = findResource('scheduler','type','jobmanager',</pre>	
See Also	Properties Function, Comma	andWindowOutput

ClusterMatlabRoot

Purpose	Specify MATLAB root for cluster	
Description	ClusterMatlabRoot specifies the pathname to MATLAB for the cluster to use for starting MATLAB worker processes. The path must be available from all nodes on which worker sessions will run. For generic schedulers, ClusterMatlabRoot is prefixed to MatlabCommandToRun.	
Characteristics	Usage	Scheduler object
	Read-only	Never
	Data type	String
Values	ClusterMatlabRoot is a string. It must be structured appropriately for the file system of the cluster nodes. The directory must be accessible as expressed in this string, from all cluster nodes on which MATLAB workers will run. If the value is empty, the MATLAB executable must be on the path of the worker.	
See Also	Properties DataLocation, MasterName, MatlabCommandToRun, PathDependencies	

Purpose	Indicate name of LSF cluster	
Description	ClusterName indicates the name of the LSF cluster on which this scheduler will run your jobs.	
Characteristics	Usage	LSF Scheduler object
	Read-only	Always
	Data type	String
See Also	Properties	MaatapNama DathDanandanajaa
	DataLocation, MasterName, PathDependencies	

CommandWindowOutput

Purpose	Indicate text produced by execution of task object's function		
Description	CommandWindowOutput contains the text produced during the execution of a task object's Function property that would normally be printed to the MATLAB Command Window.		
	the disp comma	the function specified in the Function property makes calls to and, the output that would normally be printed to the Command worker is captured in the CommandWindowOutput property.	
	Whether to store the CommandWindowOutput is specified using the CaptureCommandWindowOutput property. The CaptureCommandWindowOutput property by default is logical 0 to save network bandwidth in situations when the CommandWindowOutput is not needed.		
Characteristics	Usage	Task object	
	Read-only	Always	
	Data type	String	
Values	Before a task is evaluated, the default value of CommandWindowOutput is an empty string.		
Example	Get the Command Window output from all tasks in a job.		
	<pre>jm = findResource('scheduler','type','jobmanager',</pre>		
See Also	Properties	ureCommandWindowOutput	

Purpose	Specify configuration to apply to object or toolbox function		
Description	You use the Configuration property to apply a configuration to an object. The configuration is defined in the distcompUserConfig.m file. For details about writing and applying configurations, see "Programming with User Configurations" on page 2-44.		
	-	iguration property causes all the applicable properties nfiguration to be set on the object.	
Characteristics	Usage	Scheduler, job, or task object	
	Read-only	Never	
	Data type	String	
Values	The value of Configuration is a string that matches the name of a configuration in the file distcompUserConfig.m. If a configuration was never applied to the object, or if any of the settable object properties have been changed since a configuration was applied, the Configuration property is set to an empty string.		
Example	Use a configuration to find a scheduler.		
	jm = findRes	<pre>source('scheduler','configuration','myConfig')</pre>	
	Use a configuration when creating a job object. job1 = createJob(jm,'Configuration','jobmanager')		
	Apply a configur	ation to an existing job object.	
	job2 = creat set(job2,'Co	eJob(jm) onfiguration','myjobconfig')	
See Also	Functions		
	createJob, createParallelJob, createTask, dfeval, dfevalasync, findResource		

CreateTime

Purpose	Indicate when task or job was created	
Description		ds a date number specifying the time when a task or job was format 'day mon dd hh:mm:ss tz yyyy'.
Characteristics	Usage	Task object or job object
	Read-only	Always
	Data type	String
Values	CreateTime is assigned the job manager's system time when a task or job is created.	
Example	Create a job, then get its CreateTime.	
	<pre>jm = findResource('scheduler','type','jobmanager',</pre>	
See Also	Functions	
	createJob, cre	ateTask
	Properties	
	FinishTime, StartTime, SubmitTime	

Purpose	Indicate job whose task the worker is currently running	
Description	CurrentJob indicates the job whose task the worker is evaluating at the present time.	
Characteristics	Usage	Worker object
	Read-only	Always
	Data type	Job object
Values	CurrentJob is an empty vector while the worker is not evaluating a task.	
See Also	Properties CurrentTask, PreviousJob, PreviousTask, Worker	

CurrentTask

Purpose	Indicate task that worker is currently running	
Description	CurrentTask indicates the task that the worker is evaluating at the present time.	
Characteristics	Usage Read-only Data type	Worker object Always Task object
Values	CurrentTask is an empty vector while the worker is not evaluating a task.	
See Also	Properties CurrentJob, PreviousJob, PreviousTask, Worker	

Purpose	Specify directory where job data is stored		
Description	DataLocation id	lentifies where the job data is located.	
Characteristics	Usage Scheduler object		
	Read-only	Never	
	Data type	String or struct	
Values		a string or structure specifying a pathname for the job data. he is the directory in which MATLAB was started.	
	In a shared file system, the client, scheduler, and all worker nodes must have access to this location. In a nonshared file system, only the MATLAB client and scheduler access job data in this location.		
	Use a structure to specify the DataLocation in an environment of mixed platforms. The fields for the structure are named pc and unix. Each not uses the field appropriate for its platform. See the examples below.		
Examples	<pre>ples Set the DataLocation property for a UNIX cluster. sch = findResource('scheduler','name','LSF') set(sch, 'DataLocation','/depot/jobdata')</pre>		
	Use a structure	to set the ${\tt DataLocation}$ property for a mixed platform cluster.	
		'pc', '\\ourdomain\depot\jobdata', 'unix', '/depot/jobdata') ataLocation', d)	
See Also	Properties		
	-	ystem, PathDependencies	

EnvironmentSetMethod

Purpose	Specify means of setting environment variables for mpiexec scheduler	
Description	The mpiexec scheduler needs to supply environment variables to the MATLAB processes (labs) that it launches. There are two means by which it can do this, determined by the EnvironmentSetMethod property.	
Characteristics	Usage	mpiexec scheduler object
	Read-only	Never
	Data type	String
Values	A value of '-env' instructs the mpiexec scheduler to insert into the mpiexec command line additional directives of the form -env VARNAME value. A value of 'setenv' instructs the mpiexec scheduler to set the environment variables in the environment that launches mpiexec.	

Purpose	Indicate task error identifier	
Description	ErrorIdentifier contains the identifier output from execution of the lasterror command if an error occurs during the task evaluation.	
Characteristics	Usage	Task object
	Read-only	Always
	Data type	String
Values	ErrorIdentifier is empty before an attempt to run a task. ErrorIdentifier remains empty if the evaluation of a task object's function does not produce an error or if the error did not provide an identifier.	
See Also	Properties ErrorMessage, Function	
	211 01 m000ug0,	

ErrorMessage

Purpose	Indicate output message from task error	
Description	-	ontains the message output from execution of the lasterror error occurs during the task evaluation.
Characteristics	Usage	Task object
	Read-only	Always
	Data type	String
Values	ErrorMessage is empty before an attempt to run a task. ErrorMessage remains empty if the evaluation of a task object's function does not produce an error.	
Example	Retrieve error message from task object.	
	<pre>jm = findResource('scheduler','type','jobmanager',</pre>	
See Also	Properties ErrorIdentifi	er, Function

Purpose	Indicate directories and files that worker can access		
Description	FileDependencies contains a list of directories and files that the worker will need to access for evaluating a job's tasks.		
	The value of the property is defined by the client session. You set the value for the property as a cell array of strings. Each string is an absolute or relative pathname to a directory or file. The toolbox makes a zip file of all the files and directories referenced in the property, and stores it on the job manager machine.		
	The first time a worker evaluates a task for a particular job, the job manager passes to the worker the zip file of the files and directories in the FileDependencies property. On the worker, the file is unzipped, and a directory structure is created that is exactly the same as that accessed on the client machine where the property was set. Those entries listed in the property value are added to the path in the MATLAB worker session. (The subdirectories of the entries are not added to the path, even though they are included in the directory structure.)		
	When the worker runs subsequent tasks for the same job, it uses the directory structure already set up by the job's FileDependencies property for the first task it ran for that job.		
Characteristics	Usage	Job object	
	Read-only	After job is submitted	
	Data type	Cell array of strings	
Values	The value of FileDependencies is empty by default. If a pathname that does not exist is specified for the property value, an error is generated.		
Example	Make available to a job's workers the contents of the directories fd1 and fd2, and the file fdfile1.m.		

```
set(job1,'FileDependencies',{'fd1' 'fd2' 'fdfile1.m'})
get(job1,'FileDependencies')
ans =
    'fd1'
    'fd2'
    'fdfile1.m'
```

See Also

Functions

jobStartup, taskFinish, taskStartup

FinishedFcn

Purpose	Specify callback to execute when task or job finishes running		
Description		ll be executed in the local MATLAB session, that is, the session operty, the MATLAB client.	
Characteristics	Usage	Task object or job object	
	Read-only	Never	
	Data type	Callback	
Values	FinishedFcn ca	n be set to any valid MATLAB callback value.	
	passing to the c	llows the same model as callbacks for Handle Graphics [®] , allback function the object (job or task) that makes the call and nent of event data.	
Example	Create a job and set its FinishedFcn property using a function handle to an anonymous function that sends information to the display. jm = findResource('scheduler','type','jobmanager', 'name','MyJobManager','LookupURL','JobMgrHost'); j = createJob(jm, 'Name', 'Job_52a');		
	set(j, 'FinishedFcn', @(job,eventdata) disp([job.Name ' ' job.State]));		
	Create a task whose FinishFcn is a function handle to a separate function.		
	createTask(j, @rand, 1, {2,4}, 'FinishedFcn', @clientTaskCompleted);		
	$Create \ the \ function \ client \\ Task \\ \texttt{Completed.m} \ on \ the \ path \ of \ the \ MATLAB \ client.$		
	<pre>function clientTaskCompleted(task,eventdata) disp(['Finished task: ' num2str(task.ID)])</pre>		
	Run the job and callbacks.	l note the output messages from the job and task FinishedFcn	
	submit(j) Finished ta Job_52a fir		

FinishedFcn

See Also Properties QueuedFcn, RunningFcn

Purpose	Indicate when task or job finished		
Description	FinishTime holds a date number specifying the time when a task or job finished executing, in the format 'day mon dd hh:mm:ss tz yyyy'.		
	•	s stopped or is aborted due to an error condition, FinishTime ne when the task or job was stopped or aborted.	
Characteristics	Usage	Task object or job object	
	Read-only	Always	
	Data type	String	
Values	FinishTime is assigned the job manager's system time when the task or job has finished.		
Example	Create and subr	nit a job, then get its StartTime and FinishTime.	
	<pre>jm = findResource('scheduler','type','jobmanager',</pre>		
See Also	Functions cancel, submit		
	Properties	artTime, SubmitTime	

Function

Purpose	Indicate function called when evaluating task	
Description	Function indicates the function performed in the evaluation of a task. You set the function when you create the task using createTask.	
Characteristics	Usage Task object	
	Read-only	While task is running or finished
	Data type	String or function handle
See Also	Functions createTask	
	Properties InputArguments, NumberOfOutputArguments, OutputArguments	

Purpose	Specify whether nodes are to share DataLocation	
Description	HasSharedFilesystem determines whether the job data stored in the location identified by the DataLocation property can be accessed from all nodes in the cluster. If HasSharedFilesystem is false (0), the scheduler handles data transfers to and from the worker nodes. If HasSharedFilesystem is true (1), the workers access the job data directly.	
Characteristics	Usage	Scheduler object
	Read-only	Never
	Data type	Logical
Values	The value of HasSharedFilesystem can be set to true (or logical 1) or false (or logical 0). When you perform get on the property, the value returned is logical 1 or logical 0.	
See Also	Properties DataLocation, FileDependencies, PathDependencies	

HostAddress

Purpose	Indicate IP address of host running job manager or worker session	
Description	HostAddress indicates the numerical IP address of the computer running the job manager or worker session to which the job manager object or worker object refers. You can match the HostAddress property to find a desired job manager or worker when creating an object with findResource.	
Characteristics	Usage	Job manager object or worker object
	Read-only	Always
	Data type	Cell array of strings
Example	<pre>Create a job manager object and examine its HostAddress property. jm = findResource('scheduler','type','jobmanager', 'name','MyJobManager','LookupURL','JobMgrHost'); get(jm, 'HostAddress') ans =</pre>	
		.123.123
See Also	Functions	
	findResource	
	Properties	

HostName

Purpose	Indicate name	Indicate name of host machine running job manager or worker session	
Description	You can match the HostName property to find a desired job manager or worker when creating the job manager or worker object with findResource.		
Characteristics	Usage Read-only Data type	Job manager object or worker object Always String	
Example	Create a job manager object and examine its HostName property. jm = findResource('scheduler','type','jobmanager', 'Name', 'MyJobManager') get(jm, 'HostName') ans = JobMgrHost		
See Also	Functions findResource Properties HostAddress		

I		
Purpose	Indicate object identifier	
Description	Each object has a unique identifier within its parent object. The ID value is assigned at the time of object creation. You can use the ID property value to distinguish one object from another, such as different tasks in the same job.	
Characteristics	Usage Job object or task object	
	Read-only Always	
	Data type Double	
Values	The first job created in a job manager has the ID value of 1, and jobs are assigned ID values in numerical sequence as they are created after that.	
	The first task created in a job has the ID value of 1, and tasks are assigned ID values in numerical sequence as they are created after that.	
Example	Examine the ID property of different objects.	
	<pre>jm = findResource('scheduler','type','jobmanager',</pre>	
See Also	Functions	
	createJob, createTask	
	Properties	
	Jobs, Tasks	

Purpose	Indicate which workers are idle and available to run tasks	
Description		rs property value indicates which workers are currently job manager for the performance of job tasks.
Characteristics	Usage	Job manager object
	Read-only	Always
	Data type	Array of worker objects
Values	As workers complete tasks and assume new ones, the lists of workers in BusyWorkers and IdleWorkers can change rapidly. If you examine these two properties at different times, you might see the same worker on both lists if that worker has changed its status between those times.	
	or idle worker d	is unexpectedly, the job manager's knowledge of that as a busy oes not get updated until the job manager runs the next job and ask to that worker.
Example	Examine which perform tasks.	workers are available to a job manager for immediate use to
	-	esource('scheduler','type','jobmanager', name','MyJobManager','LookupURL','JobMgrHost'); mberOfIdleWorkers')
See Also		aximumNumberOfWorkers,MinimumNumberOfWorkers, orkers,NumberOfIdleWorkers

InputArguments

Purpose	Indicate input arguments to task object	
Description	InputArguments is a 1-by-N cell array in which each element is an expected input argument to the task function. You specify the input arguments when you create a task with the createTask function.	
Characteristics	Usage	Task object
	Read-only	While task is running or finished
	Data type	Cell array
Values	The forms and values of the input arguments are totally dependent on the task function.	
Example	<pre>Create a task requiring two input arguments, then examine the task's InputArguments property. jm = findResource('scheduler','type','jobmanager',</pre>	
See Also	Functions createTask	
	Properties Function, Outpu	utArguments

Purpose	Indicate data made available to all workers for job's tasks			
Description	The JobData property holds data that eventually gets stored in the local memory of the worker machines, so that it does not have to be passed to the worker for each task in a job that the worker evaluates. Passing the data only once per job to each worker is more efficient than passing data with each task.			
	session evaluat	Note, that to access the data contained in a job's JobData property, the worker session evaluating the task needs to have access to the job, which it gets from a call to the function getCurrentJob, as discussed in the example below.		
Characteristics	Usage	Job object		
	Read-only	After job is submitted		
	Data type	Any type		
Values	JobData is an empty vector by default.			
Example	Create job1 and set its JobData property value to the contents of array1. job1 = createJob(jm) set(job1, 'JobData', array1)			
	createTask(job1, @myfunction, 1, {task_data})			
	Now the contents of array1 will be available to all the tasks in the job. Because the job itself must be accessible to the tasks, myfunction must include a call to the function getCurrentJob. That is, the task function myfunction needs to call getCurrentJob to get the job object through which it can get the JobData property.			
See Also	Functions createJob, createTask			

Jobs

Purpose	Indicate jobs contained in job manager service or in scheduler's DataLocation		
Description	The Jobs property contains an array of all the job objects in a job manager, whether the jobs are pending, queued, running, or finished. Job objects will be categorized by their State property and job objects in the 'queued' state will be displayed in the order in which they are queued, with the next job to execute at the top (first).		
Characteristics	Usage	Job manager or scheduler object	
	Read-only	Always	
	Data type	Array of job objects	
Example	Examine the Jo objects to set pr	obs property for a job manager, and use the resulting array of coperty values.	
	<pre>jm = findResource('scheduler','type','jobmanager',</pre>		
See Also	Functions	troy, findJob, submit	
	Properties Tasks		

Purpose	Indicate name of LSF master node	
Description	MasterName indicates the name of the LSF cluster master node.	
Characteristics	Usage LSF scheduler object	
	Read-only	Always
	Data type	String
Values	MasterName is a string of the full name of the master node.	
See Also	Properties ClusterName	

MatlabCommandToRun

Purpose	Indicate MATLAB command for generic scheduler to run	
Description	MatlabCommandToRun indicates the command that the scheduler should send to a worker to start MATLAB for a task evaluation. To assure that the correct MATLAB is run, MatlablCommandToRun is prefixed by ClusterMatlabRoot.	
Characteristics	Usage Read-only Data type	Generic scheduler object Always String
Values	MatlabCommandToRun is set by the toolbox when the scheduler object is created.	
See Also	Properties ClusterMatlabRoot, SubmitFcn	

Purpose	Specify maximum number of workers to perform tasks of a job	
Description	With MaximumNumberOfWorkers you specify the greatest number of workers to be used to perform the evaluation of the job's tasks at any one time. Tasks may be distributed to different workers at different times during execution of the job, so that more than MaximumNumberOfWorkers might be used for the whole job, but this property limits the portion of the cluster used for the job at any one time.	
Characteristics	Usage	Job object
	Read-only	After job is submitted
	Data type	Double
Values	You can set the value to anything equal to or greater than the value of the MinimumNumberOfWorkers property.	
Example	Set the maximum number of workers to perform a job.	
	jm = findResource('scheduler','type','jobmanager', 'name','MyJobManager','LookupURL','JobMgrHost'); j = createJob(jm); set(j, 'MaximumNumberOfWorkers', 12);	
	-	e, the job will use no more than 12 workers, regardless of how in the job and how many workers are available on the cluster.
See Also	Properties BusyWorkers,Ic NumberOfIdleW	dleWorkers,MinimumNumberOfWorkers,NumberOfBusyWorkers, orkers

MinimumNumberOfWorkers

Purpose	Specify minimum number of workers to perform tasks of a job		
Description	With MinimumNumberOfWorkers you specify the minimum number of workers to perform the evaluation of the job's tasks. When the job is queued, it will not run until at least this many workers are simultaneously available.		
	some of the tasl number of tasks	If MinimumNumberOfWorkers workers are available to the job manager, but some of the task dispatches fail due to network or node failures, such that the number of tasks actually dispatched is less than MinimumNumberOfWorkers, the job will be cancelled.	
Characteristics	Usage	Job object	
	Read-only	After job is submitted	
	Data type	Double	
Values	The default value is 1. You can set the value anywhere from 1 up to or equal to the value of the MaximumNumberOfWorkers property.		
Example	Set the minimum number of workers to perform a job.		
	jm = findResource('scheduler','type','jobmanager', 'name','MyJobManager','LookupURL','JobMgrHost'); j = createJob(jm); set(j, 'MinimumNumberOfWorkers', 6);		
	-	e, when the job is queued, it will not begin running tasks until ers are available to perform task evaluations.	
See Also	Properties		
	BusyWorkers,I NumberOfIdleW	dleWorkers,MaximumNumberOfWorkers,NumberOfBusyWorkers, orkers	

Purpose	Specify pathname of executable mpiexec command	
Description	MpiexecFileName specifies which mpiexec command is executed to run your jobs.	
Characteristics	Usage Read-only	mpiexec scheduler object Never
	Data type	String
Remarks	See your network administrator to find out which mpiexec you should run. The default value of the property points the mpiexec included in your MATLAB installation.	
See Also	Functions mpiLibConf,mp	iSettings
	Properties SubmitArgumen	ts

Name

Purpose	Specify name for job object, or indicate name of job manager or worker object		
Description	The descriptive name of a job manager or worker is set when its service is started, as described in "Customizing Engine Services" in the MATLAB Distributed Computing Engine System Administrator's Guide. This is reflected in the Name property of the object that represents the service. You can use the name of the job manager or worker service to find the service you want when creating an object with the findResource function.		
	-	ame as a descriptive name for a job object at any time except queued or running.	
Characteristics	Usage	Job manager object, job object, or worker object	
	Read-only	Always for a job manager or worker object; after job object is submitted	
	Data type	String	
Values	By default, a job object is constructed with a Name created by concatenating the Name of the job manager with _job.		
Example	Construct a job manager object by searching for the name of the service you want to use.		
	jm = findResource('jobmanager','Name','MyJobManager');		
	Construct a job and note its default Name.		
	j = createJob(jm); get(j, 'Name') ans = MyJobManager_job		
	Change the job'	s Name property and verify the new setting.	
	set(j,'Name','MyJob') get(j,'Name') ans = MyJob		

See Also Functions findResource, createJob

NumberOfBusyWorkers

Purpose	Indicate number of workers currently running tasks	
Description	The NumberOfBusyWorkers property value indicates how many workers are currently running tasks for the job manager.	
Characteristics	Usage	Job manager object
	Read-only	Always
	Data type	Double
Values	The value of NumberOfBusyWorkers can range from 0 up to the total number of workers registered with the job manager.	
Example	Examine the number of workers currently running tasks for a job manager.	
	jm = findResource('scheduler','type','jobmanager', 'name','MyJobManager','LookupURL','JobMgrHost'); get(jm, 'NumberOfBusyWorkers')	
See Also	Properties BusyWorkers, IdleWorkers, MaximumNumberOfWorkers, MinimumNumberOfWorkers, NumberOfIdleWorkers	

Purpose	Indicate number of workers that are idle and available to run tasks	
Description	The NumberOfIdleWorkers property value indicates how many workers are currently available to the job manager for the performance of job tasks.	
		IdleWorkers is equal to or greater than the DfWorkers of the job at the top of the queue, that job can start
Characteristics	Usage	Job manager object
	Read-only	Always
	Data type	Double
Values	The value of NumberOfIdleWorkers can range from 0 up to the total number of workers registered with the job manager.	
Example	Examine the number of workers available to a job manager.	
		source('scheduler','type','jobmanager', name','MyJobManager','LookupURL','JobMgrHost'); mberOfIdleWorkers')
See Also	Properties BusyWorkers, IdleWorkers, MaximumNumberOfWorkers, MinimumNumberOfWorkers, NumberOfBusyWorkers	

NumberOfOutputArguments

Purpose	Indicate number of arguments returned by task function	
Description	v	te a task with the createTask function, you define how many nts are expected from the task function.
Characteristics	Usage	Task object
	Read-only	While task is running
	Data type	Double
Values	A matrix is con	sidered one argument.
Example	Create a task and examine its NumberOfOutputArguments property.	
	<pre>jm = findResource('scheduler','type','jobmanager',</pre>	
	NumberOfOutpu	eturns a 2-by-4 matrix, which is a single argument. The tArguments value is set by the createTask function, as the ediately after the task function definition; in this case, the 1 rand argument.
See Also	Functions createTask	
	Properties OutputArgumen	ts

Purpose	Data returned from execution of task	
Description	OutputArguments is a 1-by-N cell array in which each element corresponds to each output argument requested from task evaluation. If the task's NumberOfOutputArguments property value is 0, or if the evaluation of the task produced an error, the cell array is empty.	
Characteristics	Usage Task object	
	Read-only Always	
	Data type Cell array	
Values	The forms and values of the output arguments are totally dependent on the task function.	
Example	Create a job with a task and examine its result after running the job.	
	<pre>jm = findResource('scheduler','type','jobmanager',</pre>	
	When the job is finished, retrieve the results as a cell array.	
	result = get(t, 'OutputArguments')	
	Retrieve the results from all the tasks of a job.	
	alltasks = get(j, 'Tasks') allresults = get(alltasks, 'OutputArguments')	
	Because each task returns a cell array, allresults is a cell array of cell arrays.	
See Also	Functions createTask, getAllOutputArguments	
	Properties Function, InputArguments, NumberOfOutputArguments	

Parent

Purpose	Indicate parent object of job or task	
Description	A job's Parent property indicates the job manager or scheduler object that contains the job. A task's Parent property indicates the job object that contains the task.	
Characteristics	Usage Read-only Data type	Job object or task object Always Job manager, scheduler, or job object
See Also	Properties Jobs, Tasks	

Purpose	Specify directories to add to MATLAB worker path		
Description		PathDependencies identifies directories to be added to the path of MATLAB worker sessions for this job.	
Characteristics	Usage	Scheduler job object	
	Read-only	Never	
	Data type	Cell array of strings	
Values	PathDependencies is empty by default. For a mixed-platform environment, the strings can specify both UNIX and Windows paths; those not appropriate or not found for a particular node generate warnings and are ignored.		
Examples	Set the MATLAB worker path in a mixed-platform environment to use functions in both the central repository (/central/funcs) and the department archive (/dept1/funcs).		
	<pre>sch = findResource('scheduler','name','LSF') job1 = createJob(sch) p = {'/central/funcs','/dept1/funcs',</pre>		
See Also	Properties ClusterMatlab	Root, FileDependencies	

PreviousJob

Purpose	Indicate job whose task the worker previously ran	
Description	PreviousJob indicates the job whose task the worker most recently evaluated.	
Characteristics	Usage Worker object	
	Read-only	Always
	Data type	Job object
Values	PreviousJob is an empty vector until the worker finishes evaluating its first task.	
See Also	Properties CurrentJob, CurrentTask, PreviousTask, Worker	

Purpose	Indicate task that worker previously ran	
Description	$\ensuremath{PreviousTask}$ indicates the task that the worker most recently evaluated.	
Characteristics	Usage	Worker object
	Read-only	Always
	Data type	Task object
Values	PreviousTask is an empty vector until the worker finishes evaluating its first task.	
See Also	Properties CurrentJob, CurrentTask, PreviousJob, Worker	

QueuedFcn

Purpose	Specify M-file function to execute when job is submitted to job manager queue		
Description	QueuedFcn specifies the M-file function to execute when a job is submitted to a job manager queue.		
	The callback will be executed in the local MATLAB session, that is, the sessio that sets the property.		
Characteristics	Usage	Job object	
	Read-only	Never	
	Data type	Callback	
Values	QueuedFcn can l	be set to any valid MATLAB callback value.	
Example	Create a job and set its QueuedFcn property, using a function handle to an anonymous function that sends information to the display.		
	<pre>jm = findResource('scheduler','type','jobmanager',</pre>		
	Job_52a now	queued for execution.	
See Also	Functions submit		
	Properties FinishedFcn, Ru	unningFcn	

Purpose	Specify whether to restart MATLAB workers before evaluating tasks in job	
Description	In some cases, you might want to restart MATLAB on the workers before they evaluate any tasks in a job. This action resets defaults, clears the workspace, frees available memory, and so on.	
Characteristics	Usage	Job object
	Read-only	After job is submitted
	Data type	Logical
Values Example	Set RestartWorker to true (or logical 1) if you want the job to restart the MATLAB session on any workers before they evaluate their first task for that job. The workers are not reset between tasks of the same job. Set RestartWorker to false (or logical 0) if you do not want MATLAB restarted on any workers. When you perform get on the property, the value returned is logical 1 or logical 0. The default value is 0, which does not restart the workers. Create a job and set it so that MATLAB workers are restarted before	
-	evaluating tasks	s in a job.
	j = createJe	source('scheduler','type','jobmanager', name','MyJobManager','LookupURL','JobMgrHost'); ob(jm); tartWorker', true)
See Also	Functions submit	

RunningFcn

Purpose	Specify M-file function to execute when job or task starts running	
Description	The callback will be executed in the local MATLAB session, that is, the session that sets the property.	
Characteristics	Usage	Task object or job object
	Read-only	Never
	Data type	Callback
Values	RunningFcn can	be set to any valid MATLAB callback value.
Example	<pre>Create a job and set its QueuedFcn property, using a function handle to an anonymous function that sends information to the display. jm = findResource('scheduler','type','jobmanager',</pre>	
	submit(j) Job_52a now	
See Also	Functions submit	
	Properties FinishedFcn,Q	ueuedFcn

Purpose	Indicate when job or task started running		
Description	StartTime holds a date number specifying the time when a job or task starts running, in the format 'day mon dd hh:mm:ss tz yyyy'.		
Characteristics	Usage	Job object or task object	
	Read-only	Always	
	Data type	String	
Values	StartTime is as started running	ssigned the job manager's system time when the task or job has g.	
Example	Create and submit a job, then get its StartTime and FinishTime.		
	<pre>jm = findResource('scheduler','type','jobmanager',</pre>		
See Also	Functions submit		
	Properties CreateTime, Fi	nishTime,SubmitTime	

State

Purpose	Indicate current state of task object, job object, job manager, or worker		
Description	The State property reflects the stage of an object in its life cycle, indicating primarily whether or not it has yet been executed. The possible State values for all Distributed Computing Toolbox objects are discussed below in the "Values" section. Note The State property of the task object is different than the State property of the job object. For example, a task that is finished may be part of a job that is running if other tasks in the job have not finished.		
Characteristics	Usage Task, job, job manager, or worker object		
	Read-only Always		
	Data type String		
Values			

- running Job objects that are currently in the process of running are in the running state.
- finished Job objects that have completed running all their tasks are in the finished state.
- failed Job objects when using a third-party scheduler and the job could not run because of unexpected or missing information.
- unavailable Communication cannot be established with the job manager.

Job Manager

For a job manager, possible values for State are

- running A started job queue will execute jobs normally.
- paused The job queue is paused.
- \bullet unavailable Communication cannot be established with the job manager.

When a job manager first starts up, the default value for State is running.

Worker

For a worker, possible values for State are

- running A started job queue will execute jobs normally.
- unavailable Communication cannot be established with the worker.

Example Create a job manager object representing a job manager service, and create a job object; then examine each object's State property.

See Also Functions

createJob, createTask, findResource, pause, resume, submit

SubmitArguments

Purpose	Specify additional arguments to use when submitting job to LSF or mpiexec scheduler	
Description	SubmitArguments is simply a string that is passed via the bsub command to the LSF scheduler at submit time, or passed to the mpiexec command if using an mpiexec scheduler.	
Characteristics	Usage	LSF or mpiexec scheduler object
	Read-only	Never
	Data type	String
Values	LSF	
	Isoful SubmitArguments values might be 'm "machine1 machine2" t	

Useful SubmitArguments values might be '-m "machine1 machine2"' to indicate that your LSF scheduler should use only the named machines to run the job, or '-R "type==LINUX64"' to use only Linux 64-bit machines. Note that by default the LSF scheduler will attempt to run your job on only nodes with an architecture similar to the local machine's unless you specify '-R "type==any"'.

mpiexec

The following SubmitArguments values might be useful when using an mpiexec scheduler. They can be combined to form a single string when separated by spaces.

Value	Description
-phrase MATLAB	Use MATLAB as passphrase to connect with smpd.
-noprompt	Suppress prompting for any user information.
-localonly	Run only on the local computer.

Value	Description	
-host <hostname></hostname>	Run only on the identified host.	
-machinefile <filename></filename>	Run only on the nodes listed in the specified file (one hostname per line).	

For a complete list, see the command-line help for the mpiexec command:

mpiexec -help
mpiexec -help2

See Also

submit

Functions

Properties

MatlabCommandToRun, MpiexecFileName

SubmitFcn

Purpose	Specify function to run when job submitted to generic scheduler	
Description	SubmitFcn identifies the function to run when you submit a job to the generic scheduler. The function runs in the MATLAB client. This user-defined submit function provides certain job and task data for the MATLAB worker, and identifies a corresponding decode function for the MATLAB worker to run.	
a l		rmation, see "Using the Submit Function" on page 2-29.
Characteristics	Usage	Generic scheduler object
	Read-only	Never
	Data type	String
Values	SubmitFcn can be set to any valid MATLAB callback value that uses the user-defined submit function.	
	For a description of the user-defined submit function, how it is used, and its relationship to the worker decode function, see "Using the Submit Function" on page 2-29.	
See Also	Functions submit	
	Properties MatlabCommandToRun	

Purpose	Indicate when job was submitted to job queue	
Description		ds a date number specifying the time when a job was submitted e, in the format 'day mon dd hh:mm:ss tz yyyy'.
Characteristics	Usage	Job object
	Read-only	Always
	Data type	String
Values	SubmitTime is a submitted.	assigned the job manager's system time when the job is
Example	Create and submit a job, then get its SubmitTime.	
	<pre>jm = findResource('scheduler','type','jobmanager',</pre>	
See Also	Functions submit	
	Properties CreateTime, Fi	nishTime, StartTime

Purpose	Specify label to	associate with job object
Description	Tag is particula job object as a g callback routine	the job object with the findJob function by specifying the Tag
Characteristics	Usage Read-only Data type	Job object Never String
Values	The default val	ue is an empty string.
Example	job1 = crea You can assign set(job1,'7 You can identif property value.	job1 a unique label using Tag. Tag', 'MyFirstJob') y and access job1 using the findJob function and the Tag
See Also	Functions findJob	

Purpose	Indicate tasks	contained in job object
Description	the tasks are p	perty contains an array of all the task objects in a job, whether rending, running, or finished. Tasks are always returned in the they were created.
Characteristics	Usage	Job object
	Read-only	Always
	Data type	Array of task objects
Example	Examine the Table to bjects to set p	asks property for a job object, and use the resulting array of roperty values.
	j = create createTask createTask alltasks = alltasks = distc	(j,)
	The last line of in the job.	code sets the ${\tt Timeout}$ property value to 20 seconds for each task
See Also	Functions createTask, de	estroy,findTask
	Properties Jobs	

Timeout

Purpose	Specify time lim	it for completion of task or job
Description	Timeout holds a double value specifying the number of seconds to wait before giving up on a task or job.	
	changes from th	neout begins counting when the task State property value e Pending to Running, or when the job object State property from Queued to Running.
	stopped with the	hes out, the behavior of the task is the same as if the task were e cancel function, except a different message is placed in the corMessage property.
		es out, the behavior of the job is the same as if the job were ne cancel function, except all pending and running tasks are ng timed out.
Characteristics	Usage	Task object or job object
	Read-only	While running
	Data type	Double
Values	will never time	te for Timeout is large enough so that in practice, tasks and jobs out. You should set the value of Timeout to the number of nt to allow for completion of tasks and jobs.
Example	Set a job's Timed	out value to 1 minute.
	-	
See Also	Functions submit	
	Properties ErrorMessage, S	State

Purpose	Indicate type of object	
Description	Type indicates the type of object.	
Characteristics	Usage	Scheduler object, scheduler job object, or scheduler task object
	Read-only	Always
	Data type	String
Values	Type is a string	set to 'task', 'job', or the name of the generic scheduler.

UserData

Purpose	Specify data to a	associate with job or task object
Description	You configure UserData to store data that you want to associate with an object. The object does not use this data directly, but you can access it using the get function or dot notation.	
	UserData is stored in the local MATLAB client session, not in the job manager. So, one MATLAB client session cannot access the data stored in this property by another MATLAB client session. Even on the same machine, if you close the client session where UserData is set for an object, and then access the same object from a later client session via the job manager, the original UserData is not recovered. Likewise, commands such as	
	clear all clear funct	ions
	will clear an obj UserData prope	ect in the local session, permanently removing the data in the rty.
Characteristics	Usage	Job object or task object
	Read-only	Never
	Data type	Any type
Values	The default valu	ie is an empty vector.
Example	Suppose you cre	eate the job object job1.
	job1 = crea	teJob(jm);
	You can associa	te data with job1 by storing it in UserData.
	<pre>coeff.a = 1 coeff.b = - job1.UserDa get(job1,'U ans =</pre>	1.25; ta = coeff serData')

UserName

Purpose	Indicate user w	ho created job
Description	The UserName p who created the	property value is a string indicating the login name of the user e job.
Characteristics	Usage	Job object
	Read-only	Always
	Data type	String
Example	Examine a job t	to see who created it.
	get(job1, '	UserName')
	ans = jsmith	

Worker

Purpose	Indicate worker session that performed task	
Description	The Worker property value is an object representing the worker session that evaluated the task.	
Characteristics	Usage Read-only Data type	Task object Always Worker object
Values	Before a task is	evaluated, its Worker property value is an empty vector.
Example	submit(job1 waitForStat	:e(job1,'finished') ask(job1,'ID',1) Jame
See Also	Properties Tasks	

Purpose	Specify operating system of nodes on which mpiexec scheduler will start labs	
Description	WorkerMachineOsType specifies the operating system of the nodes that an mpiexec scheduler will start labs on for the running of a parallel job.	
Characteristics	Usage	mpiexec scheduler object
	Read-only	Never
	Data type	String
Values	running an mpi	the property can have is 'pc' or 'unix'. The nodes of the labs exec job must all be the same platform. The only heterogeneous in the cluster for the same mpiexec job is Macintosh with
See Also	Properties HostAddress, H	ostName

WorkerMachineOsType



CHECKPOINT- BASE	The name of the parameter in the mdce_def file that defines the location of the job manager and worker checkpoint directories.
checkpoint directory	Location where job manager checkpoint information and worker checkpoint information is stored.
client	The MATLAB session that defines and submits the job. This is the MATLAB session in which the programmer usually develops and prototypes applications. Also known as the MATLAB client.
client computer	The computer running the MATLAB client.
cluster	A collection of computers that are connected via a network and intended for a common purpose.
computer	A system with one or more processors.
coarse-grained application	An application for which run-time is significantly greater than the communication time needed to start and stop the program. Coarse-grained distributed applications are also called embarrassingly parallel applications.
distributed application	The same application that runs independently on several nodes, possibly with different input parameters. There is no communication, shared data, or synchronization points between the nodes. Distributed applications can be either coarse-grained or find-grained.
distributed computing	Computing with distributed applications, running the application on several nodes simultaneously.
distributed computing demos	Demonstration programs that use the Distributed Computing Toolbox, as opposed to sequential demos.
DNS	Domain Name System. A system that translates Internet domain names into IP addresses.
head node	Usually, the node of the cluster designated for running the job manager and license manager. It is often useful to run all the nonworker related processes on a single machine.
heterogeneous cluster	A cluster that is not homogeneous.
homogeneous cluster	A cluster of identical machines, in terms of both hardware and software.
job	The complete large-scale operation to perform in MATLAB, composed of a set of tasks.

Glossary-1

job manager	The MathWorks process that queues jobs and assigns tasks to workers. A third- party process that performs this function is called a scheduler. The general term "scheduler" can also refer to a job manager.
job manager checkpoint information	Snapshot of information necessary for the job manager to recover from a system crash or reboot.
job manager database	The database that the job manager uses to store the information about its jobs and tasks.
job manager lookup process	The process that allows clients, workers, and job managers to find each other. It starts automatically when the job manager starts.
lab	When workers start, they work independently by default. They can then connect to each other and work together as peers, and are then referred to as labs.
LOGDIR	The name of the parameter in the mdce_def file that defines the directory where logs are stored.
MATLAB client	See client.
MATLAB job	See job manager.
manager	See Job manager.
-	See worker.
manager	
manager MATLAB worker	See worker. The service that has to run on all machines before they can run a job manager or worker. This is the engine foundation process, making sure that the job
manager MATLAB worker	See worker. The service that has to run on all machines before they can run a job manager or worker. This is the engine foundation process, making sure that the job manager and worker processes that it controls are always running.
manager MATLAB worker mdce	See worker. The service that has to run on all machines before they can run a job manager or worker. This is the engine foundation process, making sure that the job manager and worker processes that it controls are always running. Note that the program and service name is all lower-case letters. The file that defines all the defaults for the mdce processes by allowing you to
manager MATLAB worker mdce mdce_def file	See worker. The service that has to run on all machines before they can run a job manager or worker. This is the engine foundation process, making sure that the job manager and worker processes that it controls are always running. Note that the program and service name is all lower-case letters. The file that defines all the defaults for the mdce processes by allowing you to set preferences or definitions in the form of parameter values. Message Passing Interface, the means by which labs communicate with each
manager MATLAB worker mdce mdce_def file MPI	See worker. The service that has to run on all machines before they can run a job manager or worker. This is the engine foundation process, making sure that the job manager and worker processes that it controls are always running. Note that the program and service name is all lower-case letters. The file that defines all the defaults for the mdce processes by allowing you to set preferences or definitions in the form of parameter values. Message Passing Interface, the means by which labs communicate with each other while running tasks in the same job.

register a worker	The action that happens when both worker and job manager are started and the worker contacts job manager.
scheduler	The process, either third-party or the MathWorks job manager, that queues jobs and assigns tasks to workers.
task	One segment of a job to be evaluated by a worker.
worker	The MATLAB process that performs the task computations. Also known as the MATLAB worker or worker process.
worker checkpoint information	Files required by the worker during the execution of tasks.

Glossary

Index

B

BusyWorkers property 4-8

С

cancel function 3-7 CaptureCommandWindowOutput property 4-9 clear function 3-9 ClusterMatlabRoot property 4-10 ClusterName property 4-11 CommandWindowOutput property 4-12 Configuration property 4-13 configurations 2-44 createJob function 3-10 createParallelJob function 3-12 createTask function 3-14 CreateTime property 4-14 current working directory MATLAB worker 2-47 CurrentJob property 4-15 CurrentTask property 4-16

D

DataLocation property 4-17 dctconfig function 3-16 demote function 3-18 destroy function 3-19 dfeval function 3-20 dfevalasync function 3-23

Ε

EnvironmentSetMethod property 4-18 ErrorIdentifier property 4-19 ErrorMessage property 4-20

F

FileDependencies property 4-21 files sharing 2-13 using an LSF scheduler 2-23 findJob function 3-25 findBesource function 3-27 findTask function 3-30 FinishedFcn property 4-23 FinishTime property 4-25 Function property 4-26 functions cancel 3-7 clear 3-9 createJob 3-10 createParallelJob 3-12 createTask 3-14 dctconfig 3-16 demote 3-18 destrov 3-19 dfeval 3-20 dfevalasync 3-23 findJob 3-25 findResource 3-27 findTask 3-30 get 3-32 getAllOutputArguments 3-34 getCurrentJob 3-36 getCurrentJobmanager 3-37 getCurrentTask 3-38 aetCurrentWorker 3-39 getDebugLog 3-40 gop 3-41 help 3-42 inspect 3-43 jobStartup 3-44

functions (continued) labBarrier 3-45 labBroadcast 3-46 labindex 3-48 labProbe 3-49 labReceive 3-50 labSend 3-51length 3-52 methods 3-53mpiLibConf 3-54 mpiSettings 3-55 numlabs 3-57 pause 3-58 promote 3-59 resume 3-60 set 3-61 size 3-64 submit 3-65 taskFinish 3-66 taskStartup 3-67 waitForState 3-68

G

get function 3-32
getAllOutputArguments function 3-34
getCurrentJob function 3-36
getCurrentJobmanager function 3-37
getCurrentTask function 3-38
getCurrentWorker function 3-39
getDebugLogp function 3-40
gop function 3-41

Η

HasSharedFilesystem property 4-27 help command-line 1-12 help function 3-42 HostAddress property 4-28 HostName property 4-29

I

ID property 4-30 IdleWorkers property 4-31 InputArguments property 4-32 inspect function 3-43

J

job creating example 2-11 creating on generic scheduler example 2-34 creating on LSF scheduler example 2-20 life cycle 2-3 submitting to generic scheduler queue 2-35 submitting to LSF scheduler queue 2-22 submitting to queue 2-12 job manager finding example 2-10 JobData property 4-33 Jobs property 4-34 jobStartup function 3-44

L

labBarrier function 3-45 labBroadcast function 3-46 labindex function 3-48 labProbe function 3-49 labReceive function 3-50 labSend function 3-51 length function 3-52 LSF scheduler 2-19

Μ

MasterName property 4-35 MatlabCommandToRun property 4-36 MaximumNumberOfWorkers property 4-37 methods function 3-53 MinimumNumberOfWorkers property 4-38 MpiexecFileName property 4-39 mpiLibConf function 3-54 mpiSettings function 3-55

Ν

Name property 4-40 NumberOfBusyWorkers property 4-42 NumberOfIdleWorkers property 4-43 NumberOfOutputArguments property 4-44 numlabs function 3-57

0

objects 1-7 OutputArguments property 4-45

P

parallel jobs 2-37 job manager 2-38 mpiexec scheduler 2-40 Parent property 4-46 PathDependencies property 4-47 pause function 3-58 platforms supported 1-7 PreviousJob property 4-48 PreviousTask property 4-49 programming basic session 2-9 guidelines 2-2 tips 2-47 with an LSF scheduler basic session 2-19 promote function 3-59 properties BusyWorkers 4-8 CaptureCommandWindowOutput 4-9 ClusterMatlabRoot 4-10 ClusterName 4-11 CommandWindowOutput 4-12 Configuration 4-13 CreateTime 4-14 CurrentJob 4-15 CurrentTask 4-16 DataLocation 4-17 EnvironmentSetMethod 4-18 ErrorIdentifier 4-19 ErrorMessage 4-20

properties (continued) FileDependencies 4-21 FinishedEcn 4-23 FinishTime 4-25 Function 4-26 HasSharedFilesystem 4-27 HostAddress 4-28 HostName 4-29 TD 4-30 IdleWorkers 4-31 InputArguments 4-32 JobData 4-33 Jobs 4-34 MasterName 4-35 MatlabCommandToRun 4-36 MaximumNumberOfWorkers 4-37 MinimumNumberOfWorkers 4-38 MpiexecFileName 4-39 Name 4-40 NumberOfBusyWorkers 4-42 NumberOfIdleWorkers 4-43 NumberOfOutputArguments 4-44 **OutputArguments** 4-45 Parent 4-46 PathDependencies 4-47 PreviousJob 4-48 PreviousTask 4-49 QueuedFcn 4-50 RestartWorker 4-51 RunningFcn 4-52 StartTime 4-53 State 4-54 SubmitArguments 4-56 SubmitFcn 4-58 SubmitTime 4-59 Tag 4-60 Tasks 4-61

properties (continued) Timeout 4-62 Type 4-63 UserData 4-64 UserName 4-65 Worker 4-66 WorkerMachineOsType 4-67

Q

QueuedFcn property 4-50

R

RestartWorker property 4-51 results retrieving 2-13 retrieving from job on generic scheduler 2-36 retrieving from job on LSF scheduler 2-23 resume function 3-60 RunningFcn property 4-52

S

scheduler generic 2-27 LSF 2-19 finding, example 2-19 set function 3-61 size function 3-64 StartTime property 4-53 State property 4-54 submit function 3-65 SubmitArguments property 4-56 SubmitFcn property 4-58 SubmitTime property 4-59

Index

T

Tag property 4-60 task creating example 2-12 creating on generic scheduler example 2-35 creating on LSF scheduler example 2-22 taskFinish function 3-66 Tasks property 4-61 taskStartup function 3-67 Timeout property 4-62 troubleshooting programs 2-50 Type property 4-63

U

user congifurations 2-44 UserData property 4-64 UserName property 4-65

W

waitForState function 3-68 Worker property 4-66 WorkerMachineOsType property 4-67 Index

Index-6