MATLAB® 7 3-D Visualization

MATLAB®



How to Contact The MathWorks



(a)

www.mathworks.comWebcomp.soft-sys.matlabNewsgroupwww.mathworks.com/contact_TS.htmlTechnical Support



Product enhancement suggestions Bug reports Documentation error reports Order status, license renewals, passcodes Sales, pricing, and general information



 \succ

508-647-7000 (Phone)

508-647-7001 (Fax)

The MathWorks, Inc. 3 Apple Hill Drive Natick, MA 01760-2098

For contact information about worldwide offices, see the MathWorks Web site.

3-D Visualization

© COPYRIGHT 1984–2007 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB, Simulink, Stateflow, Handle Graphics, Real-Time Workshop, and xPC TargetBox are registered trademarks, and SimBiology, SimEvents, and SimHydraulics are trademarks of The MathWorks, Inc.

Other product or brand names are trademarks or registered trademarks of their respective holders.

Patents

The MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

Revision History

March 2006	Online only
September 2006	Online only
March 2007	Online only

New for MATLAB 7.2 (Release 2006a) Revised for MATLAB 7.3 (Release 2006b) Revised for MATLAB 7.4 (Release 2007a) This publication was previously part of the Using MATLAB Graphics User Guide.

Contents

Creating 3-D Graphs

A Typical 3-D Graph	1-2
Line Plots of 3-D Data	1-4
Plotting Matrix Data	1-4
Representing a Matrix as a Surface	1-6
Mesh and Surface Plots	1-6
Visualizing Functions of Two Variables	1-7
Surface Plots of Nonuniformly Sampled Data	1-9
Parametric Surfaces	1-11
Hidden Line Removal	1-13
Coloring Mesh and Surface Plots	1-14
Coloring Techniques	1-14
Types of Color Data	1-15
Colormaps	1 - 15
Indexed Color Surfaces — Direct and Scaled Color	
Mapping	1-17
Example — Mapping Surface Curvature to Color	1-19
Altering Colormaps	1-20
Truecolor Surfaces	1-21
Texture Mapping	1-23

Defining the View

2

Viewing Overview	2-8
Positioning the Viewpoint	2-8
Setting the Aspect Ratio	2-3
Default Views	2- 4

Azimuth and Elevation2-5Defining Scenes with Camera Graphics2-9View Control with the Camera Toolbar2-10Camera Toolbar2-10Camera Motion Controls2-13Orbit Camera2-13Orbit Camera2-15Pan/Tilt Camera2-15Move Camera Horizontally/Vertically2-16Move Camera Horizontally/Vertically2-17Zoom Camera2-19Camera Roll2-19Camera Graphics Functions2-21Example — Dollying the Camera2-22Summary of Techniques2-22Implementation2-22Stifting the Volume Data2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Moving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation Without Resizing of Graphics Objects2-34Rotation Without Resizing of Graphics Objects2-34Rotation Without Resizing of Graphics Objects2-37Projection Types2-37Projection Types2-37	Setting the Viewpoint with Azimuth and Elevation	2-5
View Control with the Camera Toolbar2-10Camera Toolbar2-10Camera Motion Controls2-13Orbit Camera2-13Orbit Camera2-13Orbit Scene Light2-15Move Camera Horizontally/Vertically2-16Move Camera Forward and Backward2-17Zoom Camera2-18Camera Roll2-19Camera Graphics Functions2-21Example — Dollying the Camera2-22Summary of Techniques2-22Implementation2-22Setting Up the View2-25Setting Up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37	Azimuth and Elevation	2-5
View Control with the Camera Toolbar2-10Camera Toolbar2-10Camera Motion Controls2-13Orbit Camera2-13Orbit Camera2-13Orbit Scene Light2-15Move Camera Horizontally/Vertically2-16Move Camera Forward and Backward2-17Zoom Camera2-18Camera Roll2-19Camera Graphics Functions2-21Example — Dollying the Camera2-22Summary of Techniques2-22Implementation2-22Setting Up the View2-25Setting Up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37		
Camera Toolbar2-10Camera Motion Controls2-13Orbit Camera2-13Orbit Scene Light2-15Pan/Tilt Camera2-15Move Camera Horizontally/Vertically2-16Move Camera Forward and Backward2-17Zoom Camera2-18Camera Roll2-19Camera Graphics Functions2-21Example — Dollying the Camera2-22Summary of Techniques2-22Implementation2-22Summary of Techniques2-24Summary of Techniques2-24Graphing the Volume Data2-25Setting Up the View2-25Specifying the Light Source2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation About the Viewing Axis2-34	Defining Scenes with Camera Graphics	2-9
Camera Toolbar2-10Camera Motion Controls2-13Orbit Camera2-13Orbit Scene Light2-15Pan/Tilt Camera2-15Move Camera Horizontally/Vertically2-16Move Camera Forward and Backward2-17Zoom Camera2-18Camera Roll2-19Camera Graphics Functions2-21Example — Dollying the Camera2-22Summary of Techniques2-22Implementation2-22Summary of Techniques2-24Summary of Techniques2-24Graphing the Volume Data2-25Setting Up the View2-25Specifying the Light Source2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation About the Viewing Axis2-34		
Camera Motion Controls2-13Orbit Camera2-13Orbit Scene Light2-15Pan/Tilt Camera2-15Move Camera Horizontally/Vertically2-16Move Camera Forward and Backward2-17Zoom Camera2-18Camera Roll2-19Camera Graphics Functions2-21Example — Dollying the Camera2-22Summary of Techniques2-22Implementation2-22Summary of Techniques2-24Summary of Techniques2-24Summary of Techniques2-25Setting Up the View2-25Setting Up the View2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation About the Viewing Axis2-34View Projection Types2-37		
Orbit Camera2-13Orbit Scene Light2-15Pan/Tilt Camera2-15Move Camera Horizontally/Vertically2-16Move Camera Forward and Backward2-17Zoom Camera2-18Camera Roll2-19Camera Graphics Functions2-21Example — Dollying the Camera2-22Summary of Techniques2-22Implementation2-22Summary of Techniques2-24Graphing the Volume Data2-25Setting Up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-33Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation About the Viewing Axis2-34View Projection Types2-37		
Orbit Scene Light2-15Pan/Tilt Camera2-15Move Camera Horizontally/Vertically2-16Move Camera Forward and Backward2-17Zoom Camera2-18Camera Roll2-19Camera Graphics Functions2-21Example — Dollying the Camera2-22Summary of Techniques2-22Implementation2-22Summary of Techniques2-24Graphing the Volume Data2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Properties2-26Defining the Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation About the Viewing Axis2-37		-
Pan/Tilt Camera2-15Move Camera Horizontally/Vertically2-16Move Camera Forward and Backward2-17Zoom Camera2-18Camera Roll2-19Camera Graphics Functions2-21Example — Dollying the Camera2-22Summary of Techniques2-22Implementation2-22Summary of Techniques2-22Implementation2-22Example — Moving the Camera Through a Scene2-24Graphing the Volume Data2-25Setting Up the View2-25Specifying the Light Source2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37		
Move Camera Horizontally/Vertically2-16Move Camera Forward and Backward2-17Zoom Camera2-18Camera Roll2-19Camera Graphics Functions2-21Example — Dollying the Camera2-22Summary of Techniques2-22Implementation2-22Summary of Techniques2-22Summary of Techniques2-22Summary of Techniques2-24Summary of Techniques2-24Summary of Techniques2-25Setting Up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37	8	
Move Camera Forward and Backward2-17Zoom Camera2-18Camera Roll2-19Camera Graphics Functions2-21Example — Dollying the Camera2-22Summary of Techniques2-22Implementation2-22Summary of Techniques2-22Implementation2-22Summary of Techniques2-24Summary of Techniques2-24Graphing the Volume Data2-25Secting up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation About the Viewing Axis2-37		
Zoom Camera2-18Camera Roll2-19Camera Graphics Functions2-21Example - Dollying the Camera2-22Summary of Techniques2-22Implementation2-22Example - Moving the Camera Through a Scene2-24Summary of Techniques2-24Summary of Techniques2-25Setting Up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation About the Viewing Axis2-37		
Camera Roll2-19Camera Graphics Functions2-21Example - Dollying the Camera2-22Summary of Techniques2-22Implementation2-22Example - Moving the Camera Through a Scene2-24Summary of Techniques2-24Graphing the Volume Data2-25Setting Up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37		
Camera Graphics Functions2-21Example - Dollying the Camera2-22Summary of Techniques2-22Implementation2-22Example - Moving the Camera Through a Scene2-24Summary of Techniques2-24Graphing the Volume Data2-25Setting Up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37		
Example Dollying the Camera2-22Summary of Techniques2-22Implementation2-22Example Moving the Camera Through a Scene2-24Summary of Techniques2-24Graphing the Volume Data2-25Setting Up the View2-25Specifying the Light Source2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37		2-15
Example Dollying the Camera2-22Summary of Techniques2-22Implementation2-22Example Moving the Camera Through a Scene2-24Summary of Techniques2-24Graphing the Volume Data2-25Setting Up the View2-25Specifying the Light Source2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37		0.01
Summary of Techniques2-22Implementation2-22Implementation2-22Example — Moving the Camera Through a Scene2-24Summary of Techniques2-24Graphing the Volume Data2-25Setting Up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Kotation About the Viewing Axis2-37	Camera Graphics Functions	2-21
Summary of Techniques2-22Implementation2-22Implementation2-22Example — Moving the Camera Through a Scene2-24Summary of Techniques2-24Graphing the Volume Data2-25Setting Up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Kotation About the Viewing Axis2-37		
Implementation2-22 Example — Moving the Camera Through a Scene 2-24Summary of Techniques2-24Graphing the Volume Data2-25Setting Up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37	Example — Dollying the Camera	2-22
Example — Moving the Camera Through a Scene2-24Summary of Techniques2-24Graphing the Volume Data2-25Setting Up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37	· -	2-22
Summary of Techniques2-24Graphing the Volume Data2-25Setting Up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37	Implementation	2-22
Summary of Techniques2-24Graphing the Volume Data2-25Setting Up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37		
Graphing the Volume Data2-25Setting Up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37	Example — Moving the Camera Through a Scene	2-24
Setting Up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37	Summary of Techniques	2-24
Setting Up the View2-25Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37	Graphing the Volume Data	2-25
Specifying the Light Source2-26Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37		2-25
Selecting a Renderer2-26Defining the Camera Path as a Stream Line2-26Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34View Projection Types2-37		2-26
Implementing the Fly-Through2-27Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation About the Viewing Axis2-34View Projection Types2-37		2-26
Low-Level Camera Properties2-30Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation About the Viewing Axis2-34View Projection Types2-37		2-26
Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation About the Viewing Axis2-34View Projection Types2-37	Implementing the Fly-Through	2-27
Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation About the Viewing Axis2-34View Projection Types2-37		
Default Viewpoint Selection2-31Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation About the Viewing Axis2-34View Projection Types2-37	Low-Level Camera Properties	2-30
Moving In and Out on the Scene2-31Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation About the Viewing Axis2-34View Projection Types2-37		
Making the Scene Larger or Smaller2-33Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation About the Viewing Axis2-34View Projection Types2-37	-	2-31
Revolving Around the Scene2-34Rotation Without Resizing of Graphics Objects2-34Rotation About the Viewing Axis2-34View Projection Types2-37	•	
Rotation Without Resizing of Graphics Objects2-34Rotation About the Viewing Axis2-34View Projection Types2-37		
Rotation About the Viewing Axis2-34View Projection Types2-37		
View Projection Types 2-37		
	<u> </u>	
	View Projection Types	2.37
4	Projection Types and Camera Location	2-38

Understanding Axes Aspect Ratio	2-42
Stretch-to-Fill	2-42
Specifying Axis Scaling	2-42
Specifying Aspect Ratio	2-43
Example — axis Command Options	2-44
Additional Commands for Setting Aspect Ratio	2-46
Axes Aspect Ratio Properties	2-47
Default Aspect Ratio Selection	2-48
Overriding Stretch-to-Fill	2-51
Effects of Setting Aspect Ratio Properties	2-52
Example — Displaying Cross-Sections of Surfaces	2-55
Example — Displaying Real Objects	2-57

Lighting as a Visualization Tool

Lighting Overview	3-2
Lighting Examples	3-2
Lighting Commands	3-3
Light Objects	3-4
Adding Lights to a Scene	3-5
Illuminating Mathematical Functions	3-5
Properties That Affect Lighting	3-7
Selecting a Lighting Method	3-9
Face and Edge Lighting Methods	3-9
Reflectance Characteristics of Graphics Objects	3-11
Specular and Diffuse Reflection	3-11
Ambient Light	3-12
Specular Exponent	3-13
Specular Color Reflectance	3-14

Back Face Lighting	3-14
Positioning Lights in Data Space	3-17

Transparency

Making Objects Transparent	4-2
Specifying Transparency	4-3
Specifying a Single Transparency Value	4-6
Example — Transparent Isosurface	4-6
Mapping Data to Transparency — Alpha Data	4-8
Size of the Alpha Data Array	4-9
Mapping Alpha Data to the Alphamap	4-9
Example — Mapping Data to Color or Transparency	4-10
Selecting an Alphamap	4-12
Example — Modifying the Alphamap	4-14

Creating 3-D Models with Patches

5

5 -2
5-2
5-3
5-4
5-7
5-7
5-10
5-14 5-14
•

Patch Edge Coloring	5-16
Example — Specifying Flat Edge and Face Coloring	5-16
Coloring Edges with Shared Vertices	5-17
Interpreting Indexed and Truecolor Data	5-19
Interpreting Indexed and Truecolor Data Indexed Color Data	5-19 5-19

Volume Visualization Techniques

Overview of Volume Visualization Examples of Volume Data	6-3 6-3
Selecting Visualization Techniques	6-4
Steps to Create a Volume Visualization	6-4
Volume Visualization Functions	6-5
Functions for Scalar Data	6-5
Functions for Vector Data	6-6
Visualizing Scalar Volume Data	6-7
Techniques for Visualizing Scalar Data	6-7
Visualizing MRI Data	6-8
Example — Ways to Display MRI Data	6-8
Exploring Volumes with Slice Planes	6-14
Example — Slicing Fluid Flow Data	6-14
Modifying the Color Mapping	6-17
Connecting Equal Values with Isosurfaces	6-19
Example — Isosurfaces in Fluid Flow Data	6-19
Isocaps Add Context to Visualizations	6-21
Other Isocap Applications	6-22
Defining Isocaps	6-22

Example — Adding Isocaps to an Isosurface	6-23
Visualizing Vector Volume Data	6-26
Using Scalar Techniques with Vector Data	6-26
Specifying Starting Points for Stream Plots	6-27
Accessing Subregions of Volume Data	6-30
Stream Line Plots of Vector Data	6-32
Example	6-32
Displaying Curl with Stream Ribbons	6-35
Example	6-35
Displaying Divergence with Stream Tubes	6-38
Example	6-38
Creating Stream Particle Animations	6-41
Example	6-41
Vector Field Displayed with Cone Plots	6-44
Example	6-44

Index

Creating 3-D Graphs

A Typical 3-D Graph (p. 1-2)	The steps to follow to create a typical 3-D graph
Line Plots of 3-D Data (p. 1-4)	Line plots of data having x-, y-, and z-coordinates
Representing a Matrix as a Surface (p. 1-6)	Graphing matrix (2-D array) data on a rectangular grid
Coloring Mesh and Surface Plots (p. 1-14)	Techniques for coloring surface and mesh plots, including colormaps, truecolor, and texture mapping.

A Typical 3-D Graph

This table illustrates typical steps involved in producing 3-D scenes containing either data graphs or models of 3-D objects. Example applications include pseudocolor surfaces illustrating the values of functions over specific regions and objects drawn with polygons and colored with light sources to produce realism. Usually, you follow either step 4 or step 5.

Step	Typical Code
1 Prepare your data.	Z = peaks(20);
2 Select window and position plot region within window.	figure(1) subplot(2,1,2)
3 Call 3-D graphing function.	<pre>h = surf(Z);</pre>
4 Set colormap and shading algorithm.	<pre>colormap hot shading interp set(h,'EdgeColor','k')</pre>


Step	Typical Code		
	light('Position',[-2,2,20])		
5 Add lighting.	lighting phong		
	material([0.4,0.6,0.5,30])		
	set(h,'FaceColor',[0.7 0.7 0],		
	'BackFaceLighting','lit')		
	view([30,25])		
6 Set viewpoint.	<pre>set(gca,'CameraViewAngleMode','Manual')</pre>		
	axis([5 15 5 15 -8 8])		
7 Set axis limits and tick marks.	<pre>set(gca,'ZTickLabel','Negative Positive')</pre>		
8 Set aspect ratio.	<pre>set(gca,'PlotBoxAspectRatio',[2.5 2.5 1])</pre>		
	<pre>xlabel('X Axis')</pre>		
9 Annotate the graph	ylabel('Y Axis')		
with axis labels, legend,	zlabel('Function Value')		
and text.	title('Peaks')		
	<pre>set(gcf,'PaperPositionMode','auto')</pre>		
10 Print graph.	print -dps2		

Line Plots of 3-D Data

The 3-D analog of the plot function is plot3. If x, y, and z are three vectors of the same length,

plot3(x,y,z)

generates a line in 3-D through the points whose coordinates are the elements of x, y, and z and then produces a 2-D projection of that line on the screen. For example, these statements produce a helix.




Plotting Matrix Data

If the arguments to plot3 are matrices of the same size, MATLAB $^{\odot}$ plots lines obtained from the columns of X, Y, and Z. For example,

[X,Y] = meshgrid([-2:0.1:2]); Z = X.*exp(-X.^2-Y.^2); plot3(X,Y,Z) grid on

Notice how MATLAB cycles through line colors.



T

Representing a Matrix as a Surface

- "Mesh and Surface Plots" on page 1-6
- "Visualizing Functions of Two Variables" on page 1-7
- "Surface Plots of Nonuniformly Sampled Data" on page 1-9
- "Parametric Surfaces" on page 1-11
- "Hidden Line Removal" on page 1-13

MATLAB defines a surface by the *z*-coordinates of points above a rectangular grid in the *x*-*y* plane. The plot is formed by joining adjacent points with straight lines. Surface plots are useful for visualizing matrices that are too large to display in numerical form and for graphing functions of two variables.

MATLAB can create different forms of surface plots. Mesh plots are wire-frame surfaces that color only the lines connecting the defining points. Surface plots display both the connecting lines and the faces of the surface in color. This table lists the various forms.

Function	Used to Create		
mesh, surf	Surface plot		
meshc, surfc	Surface plot with contour plot beneath it		
meshz	Surface plot with curtain plot (reference plane)		
pcolor	Flat surface plot (value is proportional only to color)		
surfl	Surface plot illuminated from specified direction		
surface	Low-level function (on which high-level functions are based) for creating surface graphics objects		

Mesh and Surface Plots

The mesh and surf commands create 3-D surface plots of matrix data. If Z is a matrix for which the elements Z(i,j) define the height of a surface over an underlying (i,j) grid, then

```
mesh(Z)
```

generates a colored, wire-frame view of the surface and displays it in a 3-D view. Similarly,

surf(Z)

generates a colored, faceted view of the surface and displays it in a 3-D view. Ordinarily, the facets are quadrilaterals, each of which is a constant color, outlined with black mesh lines, but the shading command allows you to eliminate the mesh lines (shading flat) or to select interpolated shading across the facet (shading interp).

Surface object properties provide additional control over the visual appearance of the surface. You can specify edge line styles, vertex markers, face coloring, lighting characteristics, and so on.

Visualizing Functions of Two Variables

The first step in displaying a function of two variables, z = f(x,y), is to generate X and Y matrices consisting of repeated rows and columns, respectively, over the domain of the function. Then use these matrices to evaluate and graph the function.

The meshgrid function transforms the domain specified by two vectors, x and y, into matrices X and Y. You then use these matrices to evaluate functions of two variables. The rows of X are copies of the vector x and the columns of Y are copies of the vector y.

To illustrate the use of meshgrid, consider the sin(r)/r or sinc function. To evaluate this function between -8 and 8 in both x and y, you need pass only one vector argument to meshgrid, which is then used in both directions.

[X,Y] = meshgrid(-8:.5:8); R = sqrt(X.^2 + Y.^2) + eps;

The matrix R contains the distance from the center of the matrix, which is the origin. Adding eps prevents the divide by zero (in the next step) that produces Inf values in the data.

Forming the sinc function and plotting Z with mesh results in the 3-D surface.


$$Z = sin(R)./R;$$

Emphasizing Surface Shape

mesh(X,Y,Z)

MATLAB provides a number of techniques that can enhance the information content of your graphs. For example, this graph of the sinc function uses the same data as the previous graph, but employs lighting and view adjustment to emphasize the shape of the graphed function (daspect, axis, view, camlight).

```
surf(X,Y,Z,'FaceColor','interp',...
'EdgeColor','none',...
'FaceLighting','phong')
daspect([5 5 1])
axis tight
view(-50,30)
camlight left
```



See the surf function for more information on surface plots.

Surface Plots of Nonuniformly Sampled Data

You can use meshgrid to create a grid of uniformly sampled data points at which to evaluate and graph the sinc function. MATLAB then constructs the surface plot by connecting neighboring matrix elements to form a mesh of quadrilaterals.

To produce a surface plot from nonuniformly sampled data, first use griddata to interpolate the values at uniformly spaced points, and then use mesh and surf in the usual way.

Example – Displaying Nonuniform Data on a Surface

This example evaluates the sinc function at random points within a specific range and then generates uniformly sampled data for display as a surface plot. The process involves these tasks:

- Use linspace to generate evenly spaced values over the range of your unevenly sampled data.
- Use meshgrid to generate the plotting grid with the output of linspace.

- Use griddata to interpolate the irregularly sampled data to the regularly spaced grid returned by meshgrid.
- Use a plotting function to display the data.
- **1** First, generate unevenly sampled data within the range [-8, 8] and use it to evaluate the function.

```
x = rand(100,1)*16 - 8;
y = rand(100,1)*16 - 8;
r = sqrt(x.^2 + y.^2) + eps;
z = sin(r)./r;
```

2 The linspace function provides a convenient way to create uniformly spaced data with the desired number of elements. The following statements produce vectors over the range of the random data with the same resolution as that generated by the -8:.5:8 statement in the previous sinc example.

```
xlin = linspace(min(x),max(x),33);
ylin = linspace(min(y),max(y),33);
```

3 Now use these points to generate a uniformly spaced grid.


[X,Y] = meshgrid(xlin,ylin);

4 The key to this process is to use griddata to interpolate the values of the function at the uniformly spaced points, based on the values of the function at the original data points (which are random in this example). This statement uses a triangle-based cubic interpolation to generate the new data.

Z = griddata(x,y,z,X,Y,'cubic');

5 Plotting the interpolated and the nonuniform data produces

```
mesh(X,Y,Z) %interpolated
axis tight; hold on
plot3(x,y,z,'.','MarkerSize',15) %nonuniform
```



Parametric Surfaces

The functions that draw surfaces can take two additional vector or matrix arguments to describe surfaces with specific x and y data. If Z is an m-by-n matrix, x is an n-vector, and y is an m-vector, then

mesh(x,y,Z,C)

describes a mesh surface with vertices having color $\mathtt{C(i,j)}$ and located at the points

```
(x(j), y(i), Z(i,j))
```

where x corresponds to the columns of Z and y to its rows.

More generally, if X, Y, Z, and C are matrices of the same dimensions, then


mesh(X,Y,Z,C)

describes a mesh surface with vertices having color $\tt C(i,j)$ and located at the points

(X(i,j), Y(i,j), Z(i,j))

This example uses spherical coordinates to draw a sphere and color it with the pattern of pluses and minuses in a Hadamard matrix, an orthogonal matrix used in signal processing coding theory. The vectors theta and phi are in the range $-\pi \leq \text{theta} \leq \pi$ and $-\pi/2 \leq \text{phi} \leq \pi/2$. Because theta is a row vector and phi is a column vector, the multiplications that produce the matrices X, Y, and Z are vector outer products.

```
k = 5;
n = 2^k-1;
theta = pi*(-n:2:n)/n;
phi = (pi/2)*(-n:2:n)'/n;
X = cos(phi)*cos(theta);
Y = cos(phi)*sin(theta);
Z = sin(phi)*ones(size(theta));
colormap([0 0 0;1 1 1])
C = hadamard(2^k);
surf(X,Y,Z,C)
axis square
```




Hidden Line Removal

By default, MATLAB removes lines that are hidden from view in mesh plots, even though the faces of the plot are not colored. You can disable hidden line removal and allow the faces of a mesh plot to be transparent with the command

hidden off

This is the surface plot with hidden set to off.



Coloring Mesh and Surface Plots

- "Coloring Techniques" on page 1-14
- "Types of Color Data" on page 1-15
- "Colormaps" on page 1-15
- "Indexed Color Surfaces Direct and Scaled Color Mapping" on page 1-17
- "Example Mapping Surface Curvature to Color" on page 1-19
- "Altering Colormaps" on page 1-20
- "Truecolor Surfaces" on page 1-21
- "Texture Mapping" on page 1-23

You can enhance the information content of surface plots by controlling the way MATLAB applies color to these plots. MATLAB can map particular data values to colors specified explicitly or can map the entire range of data to a predefined range of colors called a *colormap*.

Coloring Techniques

There are three coloring techniques:

- Indexed Color -- MATLAB colors the surface plot by assigning each data point an index into the figure's colormap. The way MATLAB applies these colors depends on the type of shading used (faceted, flat, or interpolated).
- Truecolor MATLAB colors the surface plot using the explicitly specified colors (i.e., the RGB triplets). The way MATLAB applies these colors depends on the type of shading used (faceted, flat, or interpolated). To be rendered accurately, truecolor requires computers with 24-bit displays; however, MATLAB simulates truecolor on indexed systems. See the shading command for information on the types of shading.
- Texture Mapping -- Texture mapping displays a 2-D image mapped onto a 3-D surface.

Types of Color Data

The type of color data you specify (i.e., single values or RGB triplets) determines how MATLAB interprets it. When you create a surface plot, you can

- Provide no explicit color data, in which case MATLAB generates colormap indices from the *z*-data.
- Specify an array of color data that is equal in size to the *z*-data and is used for indexed colors.
- Specify an *m*-by-*n*-by-3 array of color data that defines an RGB triplet for each element in the *m*-by-*n z*-data array and is used for truecolor.

Colormaps

Each MATLAB figure window has a colormap associated with it. A colormap is simply a three-column matrix whose length is equal to the number of colors it defines. Each row of the matrix defines a particular color by specifying three values in the range 0 to 1. These values define the RGB components (i.e., the intensities of the red, green, and blue video components).

The colormap function, with no arguments, returns the current figure's colormap.

For example, the MATLAB default colormap contains $64\ colors\ and\ the\ 57th\ color$ is red.

RGB Color Components

This table lists some representative RGB color definitions.

Red	Green	Blue	Color
0	0	0	Black
1	1	1	White
1	0	0	Red
0	1	0	Green
0	0	1	Blue
1	1	0	Yellow
1	0	1	Magenta
0	1	1	Cyan
0.5	0.5	0.5	Gray
0.5	0	0	Dark red
1	0.62	0.40	Copper
0.49	1	0.83	Aquamarine

You can create colormaps with MATLAB array operations or you can use any of several functions that generate useful maps, including hsv, hot, cool, summer, and gray. Each function has an optional parameter that specifies the number of rows in the resulting map.

For example,

hot(m)

creates an m-by-3 matrix whose rows specify the RGB intensities of a map that varies from black, through shades of red, orange, and yellow, to white.

If you do not specify the colormap length, MATLAB creates a colormap the same length as the current colormap. The default colormap is jet(64).


If you use long colormaps (> 64 colors) in each of several figure windows, it might become necessary for the operating system to swap in different color lookup tables as the active focus is moved among the windows.

Displaying Colormaps

The colorbar function displays the current colormap, either vertically or horizontally, in the figure window along with your graph. For example, the statements

```
[x,y] = meshgrid([-2:.2:2]);
Z = x.*exp(-x.^2-y.^2);
surf(x,y,Z,gradient(Z))
colorbar
```

produce a surface plot and a vertical strip of color corresponding to the colormap. Note how the colorbar indicates the mapping of data value to color with the axis labels.



Indexed Color Surfaces – Direct and Scaled Color Mapping

MATLAB can use two different methods to map indexed color data to the colormap — direct and scaled.

Direct Mapping

Direct mapping uses the color data directly as indices into the colormap. For example, a value of 1 points to the first color in the colormap, a value of 2 points to the second color, and so on. If the color data is noninteger, MATLAB rounds it toward zero. Values greater than the number of colors in the colormap are set equal to the last color in the colormap (i.e., the number length(colormap)). Values less than 1 are set to 1.

Scaled Mapping

Scaled mapping uses a two-element vector [cmin cmax] (specified with the caxis command) to control the mapping of color data to the figure colormap. cmin specifies the data value to map to the first color in the colormap and cmax specifies the data value to map to the last color in the colormap. Data values in between are linearly transformed from the second to the next-to-last color, using the expression

```
colormap_index = fix((color_data-cmin)/(cmax-cmin)*cm_length)+1
```

cm_length is the length of the colormap.

By default, MATLAB sets cmin and cmax to span the range of the color data of all graphics objects within the axes. However, you can set these limits to any range of values. This enables you to display multiple axes within a single figure window and use different portions of the figure's colormap for each one. See Calculating Color Limits in Axes Properties of the Using MATLAB Graphics documentation for an example that uses color limits.

By default, MATLAB uses scaled mapping. To use direct mapping, you must turn off scaling when you create the plot. For example,

```
surf(Z,C,'CDataMapping','direct')
```

See surface for more information on specifying color data.

Specifying Indexed Colors

When creating a surface plot with a single matrix argument, surf(Z) for example, the argument Z specifies both the height and the color of the surface. MATLAB transforms Z to obtain indices into the current colormap.

With two matrix arguments, the statement

surf(Z,C)


independently specifies the color using the second argument.

Example – Mapping Surface Curvature to Color

The Laplacian of a surface plot is related to its curvature; it is positive for functions shaped like $i^2 + j^2$ and negative for functions shaped like $-(i^2 + j^2)$. The function del2 computes the discrete Laplacian of any matrix. For example, use del2 to determine the color for the data returned by peaks.

P = peaks(40); C = del2(P); surf(P,C) colormap hot


Creating a color array by applying the Laplacian to the data is useful because it causes regions with similar curvature to be drawn in the same color.



Compare this surface coloring with that produced by the statements


surf(P)
colormap hot

which use the same colormap, but map regions with similar z value (height above the x-y plane) to the same color.



Altering Colormaps

Because colormaps are matrices, you can manipulate them like other arrays. The brighten function takes advantage of this fact to increase or decrease the intensity of the colors. Plotting the values of the R, G, and B components of a colormap using rgbplot illustrates the effects of brighten.



NTSC Color Encoding

The brightness component of television signals uses the NTSC color encoding scheme.

```
b = .30*red + .59*green + .11*blue
= sum(diag([.30 .59 .11])*map')';
```

Using the nonlinear greyscale map,


```
colormap([b b b])
```


effectively converts a color image to its NTSC black-and-white equivalent.

Truecolor Surfaces

Computer systems with 24-bit displays are capable of displaying over 16 million (2^{24}) colors, as opposed to the 256 colors available on 8-bit displays. You can take advantage of this capability by defining color data directly as RGB values and eliminating the step of mapping numerical values to locations in a colormap.

Specify truecolor using an m-by-n-by-3 array, where the size of Z is m-by-n.






m-b**y**-*n* matrix defining surface plot

Corresponding *m*-by-*n*-by-3 matrix specifying truecolor for the surface plot

For example, the statements


Z = peaks(25); C(:,:,1) = rand(25); C(:,:,2) = rand(25); C(:,:,3) = rand(25); surf(Z,C)

create a plot of the peaks matrix with random coloring.



You can set surface properties as with indexed color.

surf(Z,C,'FaceColor','interp','FaceLighting','phong')
camlight right



Rendering Methods for Truecolor

MATLAB always uses either OpenGL or the Z-buffer rendering method when displaying truecolor. If the figure RendererMode property is set to auto, MATLAB automatically switches the value of the Renderer property to zbuffer whenever you specify truecolor data.

If you explicitly set Renderer to painters (this sets RendererMode to manual) and attempt to define an image, patch, or surface object using truecolor, MATLAB returns a warning and does not render the object.

See the image, patch, and surface functions for information on defining truecolor for these objects.

Texture Mapping

Texture mapping is a technique for mapping a 2-D image onto a 3-D surface by transforming color data so that it conforms to the surface plot. It allows you to apply a "texture," such as bumps or wood grain, to a surface without performing the geometric modeling necessary to create a surface with these features. The color data can also be any image, such as a scanned photograph.

Texture mapping allows the dimensions of the color data array to be different from the data defining the surface plot. You can apply an image of arbitrary


size to any surface. MATLAB interpolates texture color data so that it is mapped to the entire surface.

Example – Texture Mapping a Surface

This example creates a spherical surface using the sphere function and texture maps it with an image of the earth taken from space. Because the earth image is a view of earth from one side, this example maps the image to only one side of the sphere, padding the image data with 1s In this case, the image data is a 257-by-250 matrix, so it is padded equally on each side with two 257-by-125 matrices of 1s by concatenating the three matrices.

To use texture mapping, set the FaceColor to texturemap and assign the image to the surface's CData.

```
load earth % Load image data, X, and colormap, map
sphere; h = findobj('Type','surface');
hemisphere = [ones(257,125),...
X,...
ones(257,125)];
set(h,'CData',flipud(hemisphere),'FaceColor','texturemap')
colormap(map)
axis equal
view([90 0])
set(gca,'CameraViewAngleMode','manual')
view([65 30])
```



Defining the View

Viewing Overview (p. 2-3)	Overview of topics covered in this chapter
Setting the Viewpoint with Azimuth and Elevation (p. 2-5)	Using the simple azimuth and elevation view model to define the viewpoint, including definition and examples
Defining Scenes with Camera Graphics (p. 2-9)	Using the camera view model to control 3-D scenes (illustration defines terms)
View Control with the Camera Toolbar (p. 2-10)	Camera tools for manipulating 3–D scenes
Camera Graphics Functions (p. 2-21)	Functions that control the camera view model
Example — Dollying the Camera (p. 2-22)	Example showing how to reposition a scene when the user clicks over an image
Example — Moving the Camera Through a Scene (p. 2-24)	Example showing how to move a camera through a scene along a path traced by a stream line and showing how to move a light source with the camera
Low-Level Camera Properties (p. 2-30)	Description of the graphic object properties that control the camera

View Projection Types (p. 2-37)	Orthographic and perspective project types compared and illustrated and the interaction between camera properties and projection type
Understanding Axes Aspect Ratio (p. 2-42)	How MATLAB determines the axes aspect ratio for graphs and how you can specify aspect ratio
Axes Aspect Ratio Properties (p. 2-47)	Axes properties that control the aspect ratio and how to set them to achieve particular results

Viewing Overview

The *view* is the particular orientation you select to display your graph or graphical scene. The term *viewing* refers to the process of displaying a graphical scene from various directions, zooming in or out, changing the perspective and aspect ratio, flying by, and so on.

This section describes how to define the various viewing parameters to obtain the view you want. Generally, viewing is applied to 3-D graphs or models, although you might want to adjust the aspect ratio of 2-D views to achieve specific proportions or make a graph fit in a particular shape.

MATLAB viewing is composed of two basic areas:

- Positioning the viewpoint to orient the scene
- Setting the aspect ratio and relative axis scaling to control the shape of the objects being displayed

Positioning the Viewpoint

- Setting the Viewpoint -- Discusses how to specify the point from which you view a graph in terms of azimuth and elevation. This is conceptually simple, but does have limitations.
- Defining Scenes with Camera Graphics, View Control with the Camera Toolbar, and Camera Graphics Functions How to compose complex scenes using the MATLAB camera viewing model.
- Dollying the Camera and Moving the Camera Through a Scene --Programming techniques for moving the view around and through scenes.
- Low-Level Camera Properties The graphics properties that control the camera and illustrates the effects they cause.

Setting the Aspect Ratio

• View Projection Types -- Describes orthographic and perspective projection types and illustrates their use.

• Understanding Axes Aspect Ratio and Axes Aspect Ratio Properties — How MATLAB sets the aspect ratio of the axes and how you can select the most appropriate setting for your graphs.

Default Views

MATLAB automatically sets the view when you create a graph. The actual view that MATLAB selects depends on whether you are creating a 2- or 3-D graph. See "Default Viewpoint Selection" on page 2-31 and "Default Aspect Ratio Selection" on page 2-48 for a description of how MATLAB defines the standard view.


Setting the Viewpoint with Azimuth and Elevation

MATLAB enables you to control the orientation of the graphics displayed in an axes. You can specify the viewpoint, view target, orientation, and extent of the view displayed in a figure window. These viewing characteristics are controlled by a set of graphics properties. You can specify values for these properties directly or you can use the view command and rely on MATLAB automatic property selection to define a reasonable view.

Azimuth and Elevation

The view command specifies the viewpoint by defining azimuth and elevation with respect to the axis origin. Azimuth is a polar angle in the x-y plane, with positive angles indicating counterclockwise rotation of the viewpoint. Elevation is the angle above (positive angle) or below (negative angle) the x-y plane.

This diagram illustrates the coordinate system. The arrows indicate positive directions.



Default 2-D and 3-D Views


MATLAB automatically selects a viewpoint that is determined by whether the plot is 2-D or 3-D:

- For 2-D plots, the default is azimuth = 0° and elevation = 90° .
- For 3-D plots, the default is azimuth = -37.5° and elevation = 30°.

Examples of Views Specified with Azimuth and Elevation

For example, these statements create a 3-D surface plot and display it in the default 3-D view.

[X,Y] = meshgrid([-2:.25:2]); Z = X.*exp(-X.^2 -Y.^2); surf(X,Y,Z)




The statement

view([180 0])


sets the viewpoint so you are looking in the negative *y*-direction with your eye at the z = 0 elevation.

2-6



You can move the viewpoint to a location below the axis origin using a negative elevation.

view([-37.5 -30])



Limitations of Azimuth and Elevation


Specifying the viewpoint in terms of azimuth and elevation is conceptually simple, but it has limitations. It does not allow you to specify the actual position of the viewpoint, just its direction, and the *z*-axis is always pointing up. It does not allow you to zoom in and out on the scene or perform arbitrary rotations and translations.

MATLAB camera graphics provides greater control than the simple adjustments allowed with azimuth and elevation. The following sections discuss how to use camera properties to control the view.

Defining Scenes with Camera Graphics

When you look at the graphics objects displayed in an axes, you are viewing a scene from a particular location in space that has a particular orientation with regard to the scene. MATLAB provides functionality, analogous to that of a camera with a zoom lens, that enables you to control the view of the scene created by MATLAB.

This picture illustrates how the camera is defined in terms of properties of the axes.



View Control with the Camera Toolbar

- "Camera Toolbar" on page 2-10
- "Camera Motion Controls" on page 2-13
- "Orbit Camera" on page 2-13
- "Orbit Scene Light" on page 2-15
- "Pan/Tilt Camera" on page 2-15
- "Move Camera Horizontally/Vertically" on page 2-16
- "Move Camera Forward and Backward" on page 2-17
- "Zoom Camera" on page 2-18
- "Camera Roll" on page 2-19


The Camera toolbar enables you to perform a number of viewing operations interactively. To use the Camera toolbar,

- Display the toolbar by selecting **Camera Toolbar** from the figure window's **View** menu.
- Select the type of camera motion control you want to use.
- Position the cursor over the figure window and click, hold down the right mouse button, then move the cursor in the desired direction.

MATLAB updates the display immediately as you move the mouse.

Camera Toolbar

The toolbar contains the following parts:



- Camera Motion Controls These tools select which camera motion function to enable. You can also access the camera motion controls from the **Tools** menu.
- Principal Axis Selector Some camera controls operate with respect to a particular axis. These selectors enable you to select the principal axis or to select nonaxis constrained motion. The selectors are grayed out when not applicable to the currently selected function. You can also access the principal axis selector from the **Tools** menu.
- Scene Light The scene light button toggles a light source on or off in the scene (one light per axes).
- Projection Type You can select orthographic or perspective projection types.
- Reset and Stop Reset returns the scene to the standard 3-D view. Stop causes the camera to stop moving (this can be useful if you apply too much cursor movement). You can also access an expanded set of reset functions from the **Tools** menu.

Principal Axes

The principal axis of a scene defines the direction that is oriented upward on the screen. For example, a MATLAB surface plot aligns the up direction along the positive z-axis.


Principal axes constrain camera-tool motion along axes that are (on the screen) parallel and perpendicular to the principal axis that you select. Specifying a principal axis is useful if your data is defined with respect to a specific axis. Z is the default principal axis, because this matches the MATLAB default 3-D view.

Two of the camera tools (Orbit and Pan/Tilt) allow you to select a principal axis as well as axis-free motion. On the screen, the axes of rotation are determined by a vertical and a horizontal line, both of which pass through the point defined by the CameraTarget property and are parallel and perpendicular to the principal axis.

For example, when the principal axis is z, movement occurs about

- A vertical line that passes through the camera target and is parallel to the *z*-axis
- A horizontal line that passes through the camera target and is perpendicular to the z-axis

This means the scene (or camera, as the case may be) moves in an arc whose center is at the camera target. The following picture illustrates the rotation axes for a z principal axis.



The axes of rotation always pass through the camera target.

Optimizing for 3-D Camera Motion

When you create a plot, MATLAB displays it with an aspect ratio that fits the figure window. This behavior might not create an optimum situation for the manipulation of 3-D graphics, as it can lead to distortion as you move the camera around the scene. To avoid possible distortion, it is best to switch to a 3-D visualization mode (enabled from the command line with the command axis vis3d). When using the Camera toolbar, MATLAB automatically switches to the 3-D visualization mode, but warns you first with the following dialog box.



This dialog box appears only once per MATLAB session.

For more information about the underlying effects of related camera properties, see "Understanding Axes Aspect Ratio" on page 2-42. The next section, "Camera Motion Controls" on page 2-13, discusses how to use each tool.

Camera Motion Controls

This section discusses the individual camera motion functions selectable from the toolbar.

Note When interpreting the following diagrams, keep in mind that the camera always points towards the camera target. See "Defining Scenes with Camera Graphics" on page 2-9 for an illustration of the graphics properties involved in camera motion.


Orbit Camera



Orbit Camera rotates the camera about the *z*-axis (by default). You can select x-, y-, z-, or free-axis rotation using the Principal Axis Selectors. When using no principal axis, you can rotate about an arbitrary axis.

Graphics Properties

Orbit Camera changes the ${\tt CameraPosition}$ property while keeping the ${\tt CameraTarget}$ fixed.



Orbit Scene Light



The scene light is a light source that is placed with respect to the camera position. By default, the scene light is positioned to the right of the camera (i.e., camlight right). Orbit Scene Light changes the light's offset from the camera position. There is only one scene light; however, you can add other lights using the light command.

Toggle the scene light on and off by clicking the yellow light bulb icon.

Graphics Properties

Orbit Scene Light moves the scene light by changing the light's Position property.

Pan/Tilt Camera




Pan/Tilt Camera moves the point in the scene that the camera points to while keeping the camera fixed. The movement occurs in an arc about the *z*-axis by default. You can select *x*-, *y*-, *z*-, or free-axis rotation using the Principal Axes Selectors.

Graphics Properties

Pan/Tilt Camera moves the point in the scene that the camera is pointing to by changing the CameraTarget property.

2




Move Camera Horizontally/Vertically



Moving the cursor horizontally or vertically (or any combination of the two) moves the scene in the same direction.

Graphics Properties

The horizontal and vertical movement is achieved by moving the CameraPosition and the CameraTarget in unison along parallel lines.



Move Camera Forward and Backward




Moving the cursor up or to the right moves the camera toward the scene. Moving the cursor down or to the left moves the camera away from the scene. It is possible to move the camera through objects in the scene and to the other side of the camera target.

Graphics Properties

This function moves the CameraPosition along the line connecting the camera position and the camera target.

2




Zoom Camera



Zoom Camera makes the scene larger as you move the cursor up or to the right and smaller as you move the cursor down or to the left. Zooming does not move the camera and therefore cannot move the viewpoint through objects in the scene.

Graphics Properties

Zoom is implemented by changing the CameraViewAngle. The larger the angle, the smaller the scene appears, and vice versa.




Camera Roll



Camera Roll rotates the camera about the viewing axis, thereby rotating the view on the screen.

Graphics Properties

Camera Roll changes the CameraUpVector.



Camera Graphics Functions

The following table lists MATLAB functions that enable you to perform a number of useful camera maneuvers. The individual command descriptions provide information on using each one.

Function	Purpose
camdolly	Move camera position and target
camlookat	View specific objects
camorbit	Orbit the camera about the camera target
campan	Rotate the camera target about the camera position
campos	Set or get the camera position
camproj	Set or get the projection type (orthographic or perspective)
camroll	Rotate the camera about the viewing axis
camtarget	Set or get the camera target location
camup	Set or get the value of the camera up vector
camva	Set or get the value of the camera view angle
camzoom	Zoom the camera in or out on the scene

Example – Dollying the Camera

In the camera metaphor, a dolly is a stage that enables movement of the camera from side to side with respect to the scene. The camdolly command implements similar behavior by moving both the position of the camera and the position of the camera target in unison (or just the camera position if you so desire).

This example illustrates how to use camdolly to explore different regions of an image.

Summary of Techniques

This example uses

- ginput to obtain the coordinates of locations on the image
- The camdolly data coordinates option to move the camera and target to the new position based on coordinates obtained from ginput
- camva to zoom in and to fix the camera view angle, which is otherwise under automatic control

Implementation

First load the Cape Cod image and zoom in by setting the camera view angle (using camva).

```
load cape
image(X)
colormap(map)
axis image
camva(camva/2.5)
```

Then use ginput to select the *x*- and *y*-coordinates of the camera target and camera position.

```
while 1
 [x,y] = ginput(1);
if ~strcmp(get(gcf,'SelectionType'),'normal')
     break
end
```

```
ct = camtarget;
dx = x - ct(1);
dy = y - ct(2);
camdolly(dx,dy,ct(3),'movetarget','data')
drawnow
end
```

Example – Moving the Camera Through a Scene

- "Summary of Techniques" on page 2-24
- "Graphing the Volume Data" on page 2-25
- "Setting Up the View" on page 2-25
- "Specifying the Light Source" on page 2-26
- "Selecting a Renderer" on page 2-26
- "Defining the Camera Path as a Stream Line" on page 2-26
- "Implementing the Fly-Through" on page 2-27

A fly-through is an effect created by moving the camera through three-dimensional space, giving the impression that you are flying along with the camera as if in an aircraft. You can fly through regions of a scene that might be otherwise obscured by objects in the scene or you can fly by a scene by keeping the camera focused on a particular point.

To accomplish these effects you move the camera along a particular path, the *x*-axis for example, in a series of steps. To produce a fly-through, move both the camera position and the camera target at the same time.

The following example makes use of the fly-though effect to view the interior of an isosurface drawn within a volume defined by a vector field of wind velocities. This data represents air currents over North America.

See coneplot for a fixed visualization of the same data.

Summary of Techniques

This example employs a number of visualization techniques. It uses

- Isosurfaces and cone plots to illustrate the flow through the volume
- Lighting to illuminate the isosurface and cones in the volume
- Stream lines to define a path for the camera through the volume
- Coordinated motion of the camera position, camera target, and light

Graphing the Volume Data

The first step is to draw the isosurface and plot the air flow using cone plots.

See isosurface, isonormals, reducepatch, and coneplot for information on using these commands.

Setting the data aspect ratio (daspect) to [1,1,1] before drawing the cone plot enables MATLAB to calculate the size of the cones correctly for the final view.

```
load wind
wind_speed = sqrt(u.^2 + v.^2 + w.^2);
hpatch = patch(isosurface(x,y,z,wind_speed,35));
isonormals(x,y,z,wind_speed,hpatch)
set(hpatch,'FaceColor','red','EdgeColor','none');
[f vt] = reducepatch(isosurface(x,y,z,wind_speed,45),0.05);
daspect([1,1,1]);
hcone = coneplot(x,y,z,u,v,w,vt(:,1),vt(:,2),vt(:,3),2);
set(hcone,'FaceColor','blue','EdgeColor','none');
```

Setting Up the View

You need to define viewing parameters to ensure the scene is displayed correctly:

- Selecting a perspective projection provides the perception of depth as the camera passes through the interior of the isosurface (camproj).
- Setting the camera view angle to a fixed value prevents MATLAB from automatically adjusting the angle to encompass the entire scene as well as zooming in the desired amount (camva).

```
camproj perspective
camva(25)
```

2

Specifying the Light Source

Positioning the light source at the camera location and modifying the reflectance characteristics of the isosurface and cones enhances the realism of the scene:

- Creating a light source at the camera position provides a "headlight" that moves along with the camera through the isosurface interior (camlight).
- Setting the reflection properties of the isosurface gives the appearance of a dark interior (AmbientStrength set to 0.1) with highly reflective material (SpecularStrength and DiffuseStrength set to 1).
- Setting the SpecularStrength of the cones to 1 makes them highly reflective.

```
hlight = camlight('headlight');
set(hpatch,'AmbientStrength',.1,...
'SpecularStrength',1,...
'DiffuseStrength',1);
set(hcone,'SpecularStrength',1);
set(gcf,'Color','k')
```

Selecting a Renderer

Because this example uses lighting, MATLAB must use either zbuffer or, if available, OpenGL renderer settings. The OpenGL renderer is likely to be much faster displaying the animation; however, you need to use gouraud lighting with OpenGL, which is not as smooth as Phong lighting, which you can use with the zbuffer renderer. The two choices are

```
lighting gouraud
set(gcf,'Renderer','OpenGL')
or for zbuffer
lighting phong
```

```
set(gcf, 'Renderer', 'zbuffer')
```

Defining the Camera Path as a Stream Line

Stream lines indicate the direction of flow in the vector field. This example uses the x-, y-, and z-coordinate data of a single stream line to map a path

through the volume. The camera is then moved along this path. The tasks include

- Create a stream line starting at the point x = 80, y = 30, z = 11.
- Get the *x*-, *y*-, and *z*-coordinate data of the stream line.
- Delete the stream line (note that you could also use stream3 to calculate the stream line data without actually drawing the stream line).

```
hsline = streamline(x,y,z,u,v,w,80,30,11);
xd = get(hsline,'XData');
yd = get(hsline,'YData');
zd = get(hsline,'ZData');
delete(hsline)
```


Implementing the Fly-Through


To create a fly-through, move the camera position and camera target along the same path. In this example, the camera target is placed five elements further along the *x*-axis than the camera. A small value is added to the camera target x position to prevent the position of the camera and target from becoming the same point if the condition xd(n) = xd(n+5) should occur:

- Update the camera position and camera target so that they both move along the coordinates of the stream line.
- Move the light along with the camera.
- Call drawnow to display the results of each move.

```
for i=1:length(xd)-50
   campos([xd(i),yd(i),zd(i)])
   camtarget([xd(i+5)+min(xd)/100,yd(i),zd(i)])
   camlight(hlight,'headlight')
   drawnow
end
```

These snapshots illustrate the view at values of i equal to 10, 110, and 185.





Low-Level Camera Properties

- "Default Viewpoint Selection" on page 2-31
- "Moving In and Out on the Scene" on page 2-31
- "Making the Scene Larger or Smaller" on page 2-33
- "Revolving Around the Scene" on page 2-34
- "Rotation Without Resizing of Graphics Objects" on page 2-34
- "Rotation About the Viewing Axis" on page 2-34

Camera graphics is based on a group of axes properties that control the position and orientation of the camera. In general, the camera commands make it unnecessary to access these properties directly.

Property	Description
CameraPosition	Specifies the location of the viewpoint in axes units.
CameraPositionMode	In automatic mode, MATLAB determines the position based on the scene. In manual mode, you specify the viewpoint location.
CameraTarget	Specifies the location in the axes pointed to by the camera. Together with the CameraPosition, it defines the viewing axis.
CameraTargetMode	In automatic mode, MATLAB specifies the CameraTarget as the center of the axes plot box. In manual mode, you specify the location.
CameraUpVector	The rotation of the camera around the viewing axis is defined by a vector indicating the direction taken as up.
CameraUpVectorMode	In automatic mode, MATLAB orients the up vector along the positive <i>y</i> -axis for 2-D views and along the positive <i>z</i> -axis for 3-D views. In manual mode, you specify the direction.
CameraViewAngle	Specifies the field of view of the "lens." If you specify a value for CameraViewAngle, MATLAB overrides stretch-to-fill behavior (see "Understanding Axes Aspect Ratio" on page 2-42).

Property	Description
CameraViewAngleMode	In automatic mode, MATLAB adjusts the view angle to the smallest angle that captures the entire scene. In manual mode, you specify the angle.
	Setting CameraViewAngleMode to manual overrides stretch-to-fill behavior.
Projection	Selects either an orthographic or perspective projection.

Default Viewpoint Selection

When all the camera mode properties are set to auto (the default), MATLAB automatically controls the view, selecting appropriate values based on the assumption that you want the scene to fill the position rectangle (which is defined by the width and height components of the axes Position property).

By default, MATLAB

- Sets the CameraPosition so the orientation of the scene is the standard MATLAB 2-D or 3-D view (see the view command)
- Sets the CameraTarget to the center of the plot box
- Sets the CameraUpVector so the y-direction is up for 2-D views and the z-direction is up for 3-D views
- Sets the CameraViewAngle to the minimum angle that makes the scene fill the position rectangle (the rectangle defined by the axes Position property)
- Uses orthographic projection

This default behavior generally produces desirable results. However, you can change these properties to produce useful effects.

Moving In and Out on the Scene

You can move the camera anywhere in the 3-D space defined by the axes. The camera continues to point towards the target regardless of its position. When the camera moves, MATLAB varies the camera view angle to ensure the scene fills the position rectangle.

Moving Through a Scene

You can create a fly-by effect by moving the camera through the scene. To do this, continually change CameraPosition property, moving it toward the target. Because the camera is moving through space, it turns as it moves past the camera target. Override the MATLAB automatic resizing of the scene each time you move the camera by setting the CameraViewAngleMode to manual.

If you update the CameraPosition and the CameraTarget, the effect is to pass through the scene while continually facing the direction of movement.


If the Projection is set to perspective, the amount of perspective distortion increases as the camera gets closer to the target and decreases as it gets farther away.

Example – Moving Toward or Away from the Target

To move the camera along the viewing axis, you need to calculate new coordinates for the CameraPosition property. This is accomplished by subtracting (to move closer to the target) or adding (to move away from the target) some fraction of the total distance between the camera position and the camera target.

The function movecamera calculates a new CameraPosition that moves in on the scene if the argument dist is positive and moves out if dist is negative.

```
function movecamera(dist) %dist in the range [-1 1]
set(gca,'CameraViewAngleMode','manual')
newcp = cpos - dist * (cpos - ctarg);
set(gca,'CameraPosition',newcp)
function out = cpos
out = get(gca,'CameraPosition');
function out = ctarg
out = get(gca,'CameraTarget');
```



Note that setting the CameraViewAngleMode to manual overrides MATLAB stretch-to-fill behavior and can cause an abrupt change in the aspect ratio. See "Understanding Axes Aspect Ratio" on page 2-42 for more information on stretch-to-fill.

Making the Scene Larger or Smaller

Adjusting the CameraViewAngle property makes the view of the scene larger or smaller. Larger angles cause the view to encompass a larger area, thereby making the objects in the scene appear smaller. Similarly, smaller angles make the objects appear larger.

Changing CameraViewAngle makes the scene larger or smaller without affecting the position of the camera. This is desirable if you want to zoom in without moving the viewpoint past objects that will then no longer be in the scene (as could happen if you changed the camera position). Also, changing the CameraViewAngle does not affect the amount of perspective applied to the scene, as changing CameraPosition does when the figure Projection property is set to perspective.

Revolving Around the Scene

You can use the view command to revolve the viewpoint about the z-axis by varying the azimuth, and about the azimuth by varying the elevation. This has the effect of moving the camera around the scene along the surface of a sphere whose radius is the length of the viewing axis. You could create the same effect by changing the CameraPosition, but doing so requires you to perform calculations that MATLAB performs for you when you call view.

For example, the function orbit moves the camera around the scene.

```
function orbit(deg)
[az el] = view;
rotvec = 0:deg/10:deg;
for i = 1:length(rotvec)
      view([az+rotvec(i) el])
      drawnow
end
```

Rotation Without Resizing of Graphics Objects

When CameraViewAngleMode is auto, MATLAB calculates the CameraViewAngle so that the scene is as large as can fit in the axes position rectangle. This causes an apparent size change during rotation of the scene. To prevent resizing during rotation, you need to set the CameraViewAngleMode to manual (which happens automatically when you specify a value for the CameraViewAngle property). To do this in the orbit function, add the statement


```
set(gca,'CameraViewAngleMode','manual')
```

Rotation About the Viewing Axis

You can change the orientation of the scene by specifying the direction defined as up. By default, MATLAB defines up as the y-axis in 2-D views (the CameraUpVector is $[0 \ 1 \ 0]$) and the z-axis for 3-D views (the CameraUpVector is $[0 \ 0 \ 1]$). However, you can specify up as any arbitrary direction.

The vector defined by the CameraUpVector property forms one axis of the camera's coordinate system. Internally, MATLAB determines the actual orientation of the camera up vector by projecting the specified vector onto the plane that is normal to the camera direction (i.e., the viewing axis). This simplifies the specification of the CameraUpVector property, because it need not lie in this plane.

In many cases, you might find it convenient to visualize the desired up vector in terms of angles with respect to the axes x-, y-, and z-axis. You can then use *direction cosines* to convert from angles to vector components. For a unit vector, the expression simplifies to



where the angles α , β , and γ are specified in degrees.

```
XComponent = cos(\alpha \times (pi \quad 180));

YComponent = cos(\beta \times (pi \quad 180));

ZComponent = cos([[GAMMA]] \times (pi \quad 180));
```

(Consult a mathematics book on vector analysis for a more detailed explanation of direction cosines.)

Example - Calculating a Camera Up Vector

To specify an up vector that makes an angle of 30° with the *z*-axis and lies in the *y*-*z* plane, use the expression


2

upvec = [cos(90*(pi/180)),cos(60*(pi/180)),cos(30*(pi/180))];

and then set the CameraUpVector property.

```
set(gca,'CameraUpVector',upvec)
```

Drawing a sphere with this orientation produces




View Projection Types


MATLAB supports both orthographic and perspective projection types for displaying 3-D graphics. The one you select depends on the type of graphics you are displaying:

- orthographic projects the viewing volume as a rectangular parallelepiped (i.e., a box whose opposite sides are parallel). Relative distance from the camera does not affect the size of objects. This projection type is useful when it is important to maintain the actual size of objects and the angles between objects.
- perspective projects the viewing volume as the frustum of a pyramid (a pyramid whose apex has been cut off parallel to the base). Distance causes foreshortening; objects further from the camera appear smaller. This projection type is useful when you want to display realistic views of real objects.

By default, MATLAB displays objects using orthographic projection. You can set the projection type using the camproj command.


These pictures show a drawing of a dump truck (created with patch) and a surface plot of a mathematical function, both using orthographic projection.





If you measure the width of the front and rear faces of the box enclosing the dump truck, you'll see they are the same size. This picture looks unnatural because it lacks the apparent perspective you see when looking at real objects with depth. On the other hand, the surface plot accurately indicates the values of the function within rectangular space.

Now look at the same graphics objects with perspective added. The dump truck looks more natural because portions of the truck that are farther from the viewer appear smaller. This projection mimics the way human vision works. The surface plot, on the other hand, looks distorted.




Projection Types and Camera Location

By default, MATLAB adjusts the CameraPosition, CameraTarget, and CameraViewAngle properties to point the camera at the center of the scene and to include all graphics objects in the axes. If you position the camera so that there are graphics objects behind the camera, the scene displayed can be affected by both the axes Projection property and the figure Renderer property. The following summarizes the interactions between projection type and rendering method.


	Orthographic	Perspective
Z-buffer	CameraViewAngle determines extent of scene at CameraTarget.	CameraViewAngle determines extent of scene from CameraPosition to infinity.
Painters	All objects are displayed regardless of CameraPosition.	Not recommended if graphics objects are behind the CameraPosition.


This diagram illustrates what you see (gray area) when using orthographic projection and Z-buffer. Anything in front of the camera is visible.




Orthographic projection and Z-buffer renderer

In perspective projection, you see only what is visible in the cone of the camera view angle.





Painters rendering method is less suited to moving the camera in 3-D space because MATLAB does not clip along the viewing axis. Orthographic projection in painters method results in all objects contained in the scene being visible regardless of the camera position.



Orthographic projection and painters renderer

Printing 3-D Scenes

The same effects described in the previous section occur in hardcopy output. However, because of the differences in the process of rendering to the screen and to a printing format, MATLAB might render using Z-buffer and generate printed output using painters. You might need to specify Z-buffer printing

2-40

explicitly to obtain the results displayed on the screen (use the -zbuffer option with the print command).

Additional Information

See Basic Printing and Exporting and Selecting a Renderer in Figure Properties in the Using MATLAB Graphics documentation for information on printing and rendering methods.

Understanding Axes Aspect Ratio

- "Stretch-to-Fill" on page 2-42
- "Specifying Axis Scaling" on page 2-42
- "Specifying Aspect Ratio" on page 2-43
- "Example axis Command Options" on page 2-44
- "Additional Commands for Setting Aspect Ratio" on page 2-46

Axes shape graphics objects by setting the scaling and limits of each axis. When you create a graph, MATLAB automatically determines axis scaling based on the values or size of the plotted data, and then draws the axes to fit the space available for display. Axes aspect ratio properties control how MATLAB performs the scaling required to create a graph.

This section discusses MATLAB default behavior as well as techniques for customizing graphs.

Stretch-to-Fill

By default, the size of the axes MATLAB creates for plotting is normalized to the size of the figure window (but is slightly smaller to allow for borders). If you resize the figure, the size and possibly the aspect ratio (the ratio of width to height) of the axes changes proportionally. This enables the axes to always fill the available space in the window. MATLAB also sets the *x*-, *y*-, and *z*-axis limits to provide the greatest resolution in each direction, again optimizing the use of available space.

This stretch-to-fill behavior is generally desirable; however, you might want to control this process to produce specific results. For example, images need to be displayed in correct proportions regardless of the aspect ratio of the figure window, or you might want graphs always to be a particular size on a printed page.

Specifying Axis Scaling

The axis command enables you to adjust the scaling of graphs. By default, MATLAB finds the maxima and minima of the plotted data and chooses appropriate axes ranges. You can override the defaults by setting axis limits.

```
axis([xmin xmax ymin ymax zmin zmax])
```

You can control how MATLAB scales the axes with predefined axis options:

- axis auto returns the axis scaling to its default, automatic mode. v
 axis saves the scaling of the axes of the current plot in vector v. For subsequent graphics commands to have these same axis limits, follow them with axis(v).
- axis manual freezes the scaling at the current limits. If you then set hold on, subsequent plots use the current limits. Specifying values for axis limits also sets axis scaling to manual.
- axis tight sets the axis limits to the range of the data.
- axis ij places MATLAB into its "matrix" axes mode. The coordinate system origin is at the upper left corner. The *i*-axis is vertical and is numbered from top to bottom. The *j*-axis is horizontal and is numbered from left to right.
- axis xy places MATLAB into its default Cartesian axes mode. The coordinate system origin is at the lower left corner. The *x*-axis is horizontal and is numbered from left to right. The *y*-axis is vertical and is numbered from bottom to top.

Specifying Aspect Ratio

The axis command enables you to adjust the aspect ratio of graphs. Normally MATLAB stretches the axes to fill the window. In many cases, it is more useful to specify the aspect ratio of the axes based on a particular characteristic such as the relative length or scaling of each axis. The axis command provides a number of useful options for adjusting the aspect ratio:

- axis equal changes the current axes scaling so that equal tick mark increments on the *x*-, *y*-, and *z*-axis are equal in length. This makes the surface displayed by sphere look like a sphere instead of an ellipsoid. axis equal overrides stretch-to-fill behavior.
- axis square makes each axis the same length and overrides stretch-to-fill behavior.
- axis vis3d freezes aspect ratio properties to enable rotation of 3-D objects and overrides stretch-to-fill. Use this option after other axis options to keep settings from changing while you rotate the scene.

- axis image makes the aspect ratio of the axes the same as the image.
- axis auto returns the *x*-, *y*-, and *z*-axis limits to automatic selection mode.
- axis normal restores the current axis box to full size and removes any restrictions on the scaling of the units. It undoes the effects of axis square. Used in conjunction with axis auto, it undoes the effects of axis equal.


The axis command works by manipulating axes graphics object properties.

Example – axis Command Options


The following three pictures illustrate the effects of three axis options on a cylindrical surface created with the statements

t = 0:pi/6:4*pi; [x,y,z] = cylinder(4+cos(t),30); surf(x,y,z)


axis normal is the default behavior. MATLAB automatically sets the axis limits to span the data range along each axis and stretches the plot to fit the figure window.



axis square creates an axes that is square regardless of the shape of the figure window. The cylindrical surface is no longer distorted because it is not warped to fit the window. However, the size of one data unit is not equal along all axes (the *z*-axis spans only one unit while the *x*-axes and *y*-axes span 10 units each).



axis equal makes the length of one data unit equal along each axis while maintaining a nearly square plot box. It also prevents warping of the axis to fill the window's shape.



Additional Commands for Setting Aspect Ratio

You can control the aspect ratio of your graph in three ways:

- Specifying the relative scales of the *x*-, *y*-, and *z*-axes (data aspect ratio)
- Specifying the shape of the space defined by the axes (plot box aspect ratio)
- Specifying the axis limits

The following commands enable you to set these values.

Command	Purpose
daspect	Set or query the data aspect ratio
pbaspect	Set or query the plot box aspect ratio
xlim	Set or query <i>x</i> -axis limits
ylim	Set or query y-axis limits
zlim	Set or query <i>z</i> -axis limits

See "Axes Aspect Ratio Properties" on page 2-47 for a list of the axes properties that control aspect ratio.

Axes Aspect Ratio Properties

- "Default Aspect Ratio Selection" on page 2-48
- "Overriding Stretch-to-Fill" on page 2-51
- "Effects of Setting Aspect Ratio Properties" on page 2-52
- "Example Displaying Cross-Sections of Surfaces" on page 2-55
- "Example Displaying Real Objects" on page 2-57

The axis command works by setting various axes object properties. You can set these properties directly to achieve precisely the effect you want.

Property	Description
DataAspectRatio	Sets the relative scaling of the individual axis data values. Set DataAspectRatio to [1 1 1] to display real-world objects in correct proportions. Specifying a value for DataAspectRatio overrides stretch-to-fill behavior.
DataAspectRatioMode	In auto, MATLAB selects axis scales that provide the highest resolution in the space available.
PlotBoxAspectRatio	Sets the proportions of the axes plot box (set box to on to see the box). Specifying a value for PlotBoxAspectRatio overrides stretch-to-fill behavior.
PlotBoxAspectRatioMode	In auto, MATLAB sets the PlotBoxAspectRatio to [1 1 1] unless you explicitly set the DataAspectRatio and/or the axis limits.
Position	Defines the location and size of the axes with a four-element vector: [<i>left offset</i> , <i>bottom offset</i> , <i>width</i> , <i>height</i>].
XLim, YLim, ZLim	Sets the minimum and maximum limits of the respective axes.
XLimMode, YLimMode, ZLimMode	In auto, MATLAB selects the axis limits.

By default, MATLAB automatically determines values for all of these properties (i.e., all the modes are auto) and then applies stretch-to-fill. You can override any property's automatic operation by specifying a value for the property or setting its mode to manual. The value you select for a particular property depends primarily on what type of data you want to display.

Much of the data visualized with MATLAB is either

- Numerical data displayed as line or mesh plots
- Representations of real-world objects (e.g., a dump truck or a section of the earth's topography)

In the first case, it is generally desirable to select axis limits that provide good resolution in each axis direction and to fill the available space. Real-world objects, on the other hand, need to be represented accurately in proportion, regardless of the angle of view.


Default Aspect Ratio Selection

There are two key elements to MATLAB default behavior — normalizing the axes size to the window size and stretch-to-fill.


The axes Position property specifies the location and dimensions of the axes. The third and fourth elements of the Position vector (width and height) define a rectangle in which MATLAB draws the axes (indicated by the dotted line in the following pictures). MATLAB stretches the axes to fill this rectangle.

The default value for the axes Units property is normalized to the parent figure dimensions. This means the shape of the figure window determines the shape of the position rectangle. As you change the size of the window, MATLAB reshapes the position rectangle to fit it.

2-48



The view is the 2-D projection of the plot box onto the screen.




As you can see, reshaping the axes to fit into the figure window can change the aspect ratio of the graph. MATLAB applies stretch-to-fill so the axes fill the position rectangle and in the process can distort the shape. This is generally desirable for graphs of numeric data, but not for displaying objects realistically.

Example – MATLAB Defaults

MATLAB surface plots are well suited for visualizing mathematical functions of two variables. For example, to display a mesh plot of the function $z = xe^{(-x^2 - y^2)}$ evaluated over the range $-2 \le x \le 2$, $-4 \le y \le 4$, use the statements

```
[X,Y] = meshgrid([-2:.15:2],[-4:.3:4]);
Z = X.*exp(-X.^2 - Y.^2);
mesh(X,Y,Z)
```



The MATLAB default property values are designed to

- Select axis limits to span the range of the data (XLimMode, YLimMode, and ZLimMode are set to auto).
- Provide the highest resolution in the available space by setting the scale of each axis independently (DataAspectRatioMode and the PlotBoxAspectRatioMode are set to auto).
- Draw axes that fit the position rectangle by adjusting the CameraViewAngle and then stretch-to-fill the axes if necessary.


Overriding Stretch-to-Fill

To maintain a particular shape, you can specify the size of the axes in absolute units such as inches, which are independent of the figure window size. However, this is not a good approach if you are writing an M-file that you want to work with a figure window of any size. A better approach is to specify the aspect ratio of the axes and override automatic stretch-to-fill.

In cases where you want a specific aspect ratio, you can override stretching by specifying a value for these axes properties:

- DataAspectRatio or DataAspectRatioMode
- PlotBoxAspectRatio or PlotBoxAspectRatioMode
- CameraViewAngle or CameraViewAngleMode

The first two sets of properties affect the aspect ratio directly. Setting either of the mode properties to manual simply disables stretch-to-fill while maintaining all current property values. In this case, MATLAB enlarges the axes until one dimension of the position rectangle constrains it.



Setting the CameraViewAngle property disables stretch-to-fill, and also prevents MATLAB from readjusting the size of the axes if you change the view.

Effects of Setting Aspect Ratio Properties

It is important to understand how properties interact with each other, in order to obtain the results you want. The DataAspectRatio, PlotBoxAspectRatio, and the *x*-, *y*-, and *z*-axis limits (XLim, YLim, and ZLim properties) all place constraints on the shape of the axes.

Data Aspect Ratio

The DataAspectRatio property controls the ratio of the axis scales. For a mesh plot of the function $\mathcal{Z} = xe^{(-x^2 - y^2)}$ evaluated over the range $-2 \le x \le 2, -4 \le y \le 4$


```
[X,Y] = meshgrid([-2:.15:2],[-4:.3:4]);
Z = X.*exp(-X.^2 - Y.^2);
mesh(X,Y,Z)
```

the values are

This means that four units in length along the *x*-axis cover the same data values as eight units in length along the *y*-axis and one unit in length along the *z*-axis. The axes fill the plot box, which has an aspect ratio of $[1 \ 1 \ 1]$ by default.

If you want to view the mesh plot so that the relative magnitudes along each axis are equal with respect to each other, you can set the DataAspectRatio to [1 1 1].

```
set(gca, 'DataAspectRatio',[1 1 1])
```



Setting the value of the DataAspectRatio property also sets the DataAspectRatioMode to manual and overrides stretch-to-fill so the specified aspect ratio is achieved.

Plot Box Aspect Ratio

Looking at the value of the PlotBoxAspectRatio for the graph in the previous section shows that it has now taken on the former value of the DataAspectRatio.


MATLAB has rescaled the plot box to accommodate the graph using the specified DataAspectRatio.

The PlotBoxAspectRatio property controls the shape of the axes plot box. MATLAB sets this property to [1 1 1] by default and adjusts the DataAspectRatio property so that graphs fill the plot box if stretching is on, or until reaching a constraint if stretch-to-fill has been overridden. When you set the value of the DataAspectRatio and thereby prevent it from changing, MATLAB varies the PlotBoxAspectRatio instead. If you specify both the DataAspectRatio and the PlotBoxAspectRatio, MATLAB is forced to change the axis limits to obey the two constraints you have already defined.

Continuing with the mesh example, if you set both properties,

```
set(gca,'DataAspectRatio',[1 1 1],...
'PlotBoxAspectRatio',[1 1 1])
```

MATLAB changes the axis limits to satisfy the two constraints placed on the axes.



Adjusting Axis Limits


MATLAB enables you to set the axis limits to the values you want. However, specifying a value for DataAspectRatio, PlotBoxAspectRatio, and the axis limits overconstrains the axes definition. For example, it is not possible for MATLAB to draw the axes if you set these values:

```
set(gca,'DataAspectRatio',[1 1 1],...
'PlotBoxAspectRatio',[1 1 1],...
```

```
'XLim',[-4 4],...
'YLim',[-4 4],...
'ZLim',[-1 1])
```

In this case, MATLAB ignores the setting of the PlotBoxAspectRatio and determines its value automatically. These particular values cause the PlotBoxAspectRatio to return to its calculated value.

MATLAB can now draw the axes using the specified DataAspectRatio and axis limits.



Example – Displaying Cross-Sections of Surfaces


Sometimes projecting a 3-D surface onto an x-, y-, or z-axis can aid visualization. To do this, you might change the aspect ratio, in order to make space for the projection. The following example illustrates how to do this:

1 Create an *x*-*y* grid and *z*-values for it:

```
[x,y] = meshgrid([-2:.2:2]);
Z = x.*exp(-x.^2-y.^2);
```

2 Plot the surface in 3-D; annotate with a colorbar and axis labels:

```
surf(x,y,Z,gradient(Z))
colorbar
xlabel('X-AXIS')
ylabel('Y-AXIS')
zlabel('Z-AXIS')
```




3 Use axis to change the Ymax value in to 3, stretching the plot in one direction:

axis([-2 2 -2 3 -0.5 0.5]) %

4 Regrid the surface, setting all Y-values equal to 3:

y = 3*ones(21);

5 Plaster a plot of the surface onto the Y-axis:




hold on

Example – Displaying Real Objects

If you want to display an object so that it looks realistic, you need to change MATLAB defaults. For example, this data defines a wedge-shaped patch object.

vertex	_list =	=	vertex_	connec	ction =	=
-	-	-	1	2	3	4
0	0	0	2	6	7	3
0	1	0	4	3	7	8
1	1	0	1	5	8	4
1	0	0	1	2	6	5
0	0	1	5	6	7	8
0	1	1	Ū.	0		
1	1	4				
1	0	4				


patch('Vertices',vertex_list,'Faces',vertex_connection,...




However, this axes distorts the actual shape of the solid object defined by the data. To display it in correct proportions, set the DataAspectRatio.

```
set(gca, 'DataAspectRatio',[1 1 1])
```

The units are now equal in the *x*-, *y*-, and *z*-directions and the axes is not being stretched to fill the position rectangle, revealing the true shape of the object.





Lighting as a Visualization Tool

Lighting Overview (p. 3-2)	Contains links to examples throughout the graphics documentation that illustrate the use of lighting
Lighting Commands (p. 3-3)	Commands for creating lighting effects
Light Objects (p. 3-4)	Creation and properties of light objects
Adding Lights to a Scene (p. 3-5)	Examples of how to position lights and set properties
Properties That Affect Lighting (p. 3-7)	Properties of axes, patches, and surfaces that affect lights
Selecting a Lighting Method (p. 3-9)	Illustration of various lighting methods showing which to use
Reflectance Characteristics of Graphics Objects (p. 3-11)	Catalog illustrating various lighting characteristics

Lighting Overview

Lighting is a technique for adding realism to a graphical scene. It does this by simulating the highlights and dark areas that occur on objects under natural lighting (e.g., the directional light that comes from the sun). To create lighting effects, MATLAB defines a graphics object called a light. MATLAB applies lighting to surface and patch objects.

Lighting Examples

These examples illustrate the use of lighting in a visualization context.

- Tracing a stream line through a volume Sets properties of surfaces, patches, and lights (MATLAB Graphics documentation).
- Using slice planes and cone plots Sets lighting characteristics of objects in a scene independently to achieve a desired result (MATLAB coneplot function).
- Lighting multiple slice planes independently to visualize fluid flow (MATLAB Graphics documentation).
- Combining single-color lit surfaces with interpolated coloring. See "Example — Visualizing MRI Data" (3–D Visualization documentation).
- Employing lighting to reveal surface shape. The fluid flow isosurface example and the surface plot of the sinc function examples illustrate this technique (3–D Visualization documentation).

Lighting Commands

MATLAB provides commands that enable you to position light sources and adjust the characteristics of lit objects. These commands include the following.

Command	Purpose
camlight	Create or move a light with respect to the camera position
lightangle	Create or position a light in spherical coordinates
light	Create a light object
lighting	Select a lighting method
material	Set the reflectance properties of lit objects

You might find it useful to set light or lit-object properties directly to achieve specific results. In addition to the material in this topic area, you can explore the following lighting examples as an introduction to lighting for visualization.

Light Objects

You create a light object using the light function. Three important light object properties are

- Color Color of the light cast by the light object
- Style Either infinitely far away (the default) or local
- Position Direction (for infinite light sources) or the location (for local light sources)

The Color property determines the color of the directional light from the light source. The color of an object in a scene is determined by the color of the object and the light source.

The Style property determines whether the light source is a point source (Style set to local), which radiates from the specified position in all directions, or a light source placed at infinity (Style set to infinite), which shines from the direction of the specified position with parallel rays.

The Position property specifies the location of the light source in axes data units. In the case of a light source at infinity, Position specifies the direction to the light source.


Lights affect surface and patch objects that are in the same axes as the light. These objects have a number of properties that alter the way they look when illuminated by lights.

Adding Lights to a Scene

This example displays the membrane surface and illuminates it with a light source emanating from the direction defined by the position vector [0 -2 1]. This vector defines a direction from the axes origin passing through the point with the coordinates 0, -2, 1. The light shines from this direction toward the axes origin.

```
membrane
light('Position',[0 -2 1])
```

Creating a light activates a number of lighting-related properties controlling characteristics such as the ambient light and reflectance properties of objects. It also switches to Z-buffer renderer if not already in that mode.



Illuminating Mathematical Functions


Lighting can enhance surface graphs of mathematical functions. For example, use the ezsurf command to evaluate the expression $\sin(\sqrt{x^2 + y^2}) \div \sqrt{x^2 + y^2}$ over the region -6π to 6π .

```
ezsurf('sin(sqrt(x^2+y^2))/sqrt(x^2+y^2)',[-6*pi,6*pi])
```



Now add lighting using the lightangle command, which accepts the light position in terms of azimuth and elevation.

```
view(0,75)
shading interp
lightangle(-45,30)
set(gcf,'Renderer','zbuffer')
set(findobj(gca,'type','surface'),...
'FaceLighting','phong',...
'AmbientStrength',.3,'DiffuseStrength',.8,...
'SpecularStrength',.9,'SpecularExponent',25,...
'BackFaceLighting','unlit')
```



After obtaining the surface object's handle using findobj, you can set properties that affect how the light reflects from the surface. See "Properties That Affect Lighting" on page 3-7 for more detailed descriptions of these properties.

Properties That Affect Lighting

You cannot see light objects themselves, but you can see their effects on any patch and surface objects present in the axes containing the light. A number of functions create these objects, including surf, mesh, pcolor, fill, and fill3 as well as the surface and patch functions.

You control lighting effects by setting various axes, light, patch, and surface object properties. All properties have default values that generally produce desirable results. However, you can achieve the specific effect you want by adjusting the values of these properties.

Property	Effect
AmbientLightColor	An axes property that specifies the color of the background light in the scene, which has no direction and affects all objects uniformly. Ambient light effects occur only when there is a visible light object in the axes.
AmbientStrength	A patch and surface property that determines the intensity of the ambient component of the light reflected from the object.
DiffuseStrength	A patch and surface property that determines the intensity of the diffuse component of the light reflected from the object.
SpecularStrength	A patch and surface property that determines the intensity of the specular component of the light reflected from the object.
SpecularExponent	A patch and surface property that determines the size of the specular highlight.
SpecularColorReflectance	A patch and surface property that determines the degree to which the specularly reflected light is colored by the object color or the light source color.
FaceLighting	A patch and surface property that determines the method used to calculate the effect of the light on the faces of the object. Choices are either no lighting, or flat, Gouraud, or Phong lighting algorithms.
EdgeLighting	A patch and surface property that determines the method used to calculate the effect of the light on the edges of the object. Choices are either no lighting, or flat, Gouraud, or Phong lighting algorithms.

Property	Effect
BackFaceLighting	A patch and surface property that determines how faces are lit when their vertex normals point away from the camera. This property is useful for discriminating between the internal and external surfaces of an object.
FaceColor	A patch and surface property that specifies the color of the object faces.
EdgeColor	A patch and surface property that specifies the color of the object edges.
VertexNormals	A patch and surface property that contains normal vectors for each vertex of the object. MATLAB uses vertex normal vectors to perform lighting calculations. While MATLAB automatically generates this data, you can also specify your own vertex normals.
NormalMode	A patch and surface property that determines whether MATLAB recalculates vertex normals if you change object data (auto) or uses the current values of the VertexNormals property (manual). If you specify values for VertexNormals, MATLAB sets this property to manual.

For more information, see descriptions of axes, surface, and patch object properties.

Selecting a Lighting Method


When you add lights to an axes, MATLAB determines the effects these lights have on the patch and surface objects that are displayed in that axes. There are different methods used to calculate the face and edge coloring of lit objects, and the one you select depends on the results you want to obtain.

Face and Edge Lighting Methods

MATLAB supports three different algorithms for lighting calculations, selected by setting the FaceLighting and EdgeLighting properties of each patch and surface object in the scene. Each algorithm produces somewhat different results:

- Flat lighting Produces uniform color across each of the faces of the object. Select this method to view faceted objects.
- Gouraud lighting Calculates the colors at the vertices and then interpolates colors across the faces. Select this method to view curved surfaces.
- Phong lighting Interpolates the vertex normals across each face and calculates the reflectance at each pixel. Select this choice to view curved surfaces. Phong lighting generally produces better results than Gouraud lighting, but takes longer to render.

This illustration shows how a red sphere looks using each of the lighting methods with one white light source.



The lighting command (as opposed to the light function) provides a convenient way to set the lighting method.

Reflectance Characteristics of Graphics Objects

You can modify the reflectance characteristics of patch and surface objects and thereby change the way they look when lights are applied to the scene. The characteristics discussed in this section include


- "Specular and Diffuse Reflection" on page 3-11
- "Ambient Light" on page 3-12
- "Specular Exponent" on page 3-13
- "Specular Color Reflectance" on page 3-14
- "Back Face Lighting" on page 3-14
- "Positioning Lights in Data Space" on page 3-17

It is likely you will adjust these characteristics in combination to produce particular results.

Also see the material command for a convenient way to produce certain lighting effects.

Specular and Diffuse Reflection

You can control the amount of specular and diffuse reflection from the surface of an object by setting the SpecularStrength and DiffuseStrength properties. This picture illustrates various settings.




SpecularStrength

Ambient Light

Ambient light is a directionless light that shines uniformly on all objects in the scene. Ambient light is visible only when there are light objects in the axes. There are two properties that control ambient light — AmbientLightColor is an axes property that sets the color, and AmbientStrength is a property of patch and surface objects that determines the intensity of the ambient light on the particular object.

This illustration shows three different ambient light colors at various intensities. The sphere is red and there is a white light object present.




AmbientStrength

The green $[0\ 1\ 0]$ ambient light does not affect the scene because there is no red component in green light. However, the color defined by the RGB values $[.5\ 0\ 1]$ does have a red component, so it contributes to the light on the sphere (but less than the white $[1\ 1\ 1]$ ambient light).

Specular Exponent


The size of the specular highlight spot depends on the value of the patch and surface object's SpecularExponent property. Typical values for this property range from 1 to 500, with normal objects having values in the range 5 to 20.

This illustration shows a red sphere illuminated by a white light with three different values for the SpecularExponent property.




Specular Color Reflectance

The color of the specularly reflected light can range from a combination of the color of the object and the color of the light source to the color of the light source only. The patch and surface SpecularColorReflectance property controls this color. This illustration shows a red sphere illuminated by a white light. The values of the SpecularColorReflectance property range from 0 (object and light color) to 1 (light color).



Back Face Lighting

Back face lighting is useful for showing the difference between internal and external faces. These pictures of cut-away cylindrical surfaces illustrate the effects of back face lighting.




BackFaceLighting = reverselit

BackFaceLighting = unlit


The default value for BackFaceLighting is reverselit. This setting reverses the direction of the vertex normals that face away from the camera, causing the interior surface to reflect light towards the camera. Setting BackFaceLighting to unlit disables lighting on faces with normals that point away from the camera.

You can also use BackFaceLighting to remove edge effects for closed objects. These effects occur when BackFaceLighting is set to reverselit and pixels along the edge of a closed object are lit as if their vertex normals faced the camera. This produces an improperly lit pixel because the pixel is visible but is really facing away from the camera.

To illustrate this effect, the next picture shows a blowup of the edge of a lit sphere. Setting BackFaceLighting to lit prevents the improper lighting of pixels.



BackFaceLighting = reverselit



BackFaceLighting = lit

Positioning Lights in Data Space


This example creates a sphere and a cube to illustrate the effects of various properties on lighting. The variables vert and fac define the cube using the patch function.

vert	=			fac	=			
	1 2 2 1 2 2	1 2 1 1 2 2 1	1 1 1 2 2 2 2		1 2 4 1 5	2 6 3 5 2 6	3 7 8 6 7	4 3 8 4 5 8
h = set hol pat lig mat axi	(h,'Fac 'Fac 'Edg 'Bac d on ch('fac ht('Pos	j('Type' eLightir eColor', eColor', kFaceLig es',fac, ition',[ition',[hiny	<pre>,'surface'); ng','phong', 'interp', [.4 .4 .4], phting','lit') 'vertices',vert; 1 3 2]); -3 -1 3]);</pre>	,'Face	eColor	','y')	;	

All faces of the cube have FaceColor set to yellow. The sphere function creates a spherical surface and the handle of this surface is obtained using findobj to search for the object whose Type property is surface. The light functions define two white (the default color) light objects located at infinity in the direction specified by the Position vectors. These vectors are defined in axes coordinates [x, y, z].

The patch uses flat FaceLighting (the default) to enhance the visibility of each side. The surface uses phong FaceLighting because it produces the smoothest interpolation of lighting effects. The material shiny command affects the reflectance properties of both the cube and sphere (although its effects are noticeable only on the sphere because of the cube's flat shading).

Because the sphere is closed, the BackFaceLighting property is changed from its default setting, which reverses the direction of vertex normals that face away from the camera, to normal lighting, which removes undesirable edge effects.



Examining the code in the lighting and material M-files can help you understand how various properties affect lighting.

Transparency

Making Objects Transparent (p. 4-2)	Overview of the object properties that specify transparency
Specifying a Single Transparency Value (p. 4-6)	How to specify a transparency value that applies to all the faces of a graphics object
Mapping Data to Transparency — Alpha Data (p. 4-8)	How to use transparency as another dimension for visualizing data
Selecting an Alphamap (p. 4-12)	Characteristics of various alphamaps and illustrations of the effects they produce

Making Objects Transparent


Making graphics objects semitransparent is a useful technique in 3-D visualization to make it possible to see an object, while at the same time, see what information the object would obscure if it was completely opaque. You can also use transparency as another dimension for displaying data, much the way color is used in MATLAB.

The transparency of a graphics object determines the degree to which you can see through the object. You can specify a continuous range of transparency varying from completely transparent (i.e., invisible) to completely opaque (i.e., no transparency).

Objects that support transparency are

- Image
- Patch
- Surface

The following picture illustrates the effect of transparency. The green isosurface (patch object) reveals the cone plot that lies in the interior.



Note You must have OpenGL available on your system to use transparency. MATLAB automatically uses OpenGL if it is available. See the figure RendererMode property for more information.

Specifying Transparency

Transparency values, which range from [0 1], are referred to as *alpha* values. An alpha value of 0 means completely transparent (i.e., invisible); an alpha value of 1 means completely opaque (i.e., no transparency).

MATLAB treats transparency in a way that is analogous to how it treats color for the respective objects:

- Patches and surfaces can define a single face and edge alpha value or use flat or interpolated transparency based on values in the figure's alphamap.
- Images, patches, and surfaces can define alpha data that is used as indices into the alphamap or directly as alpha values.
- Axes define alpha limits that control the mapping of object data to alpha values.
- Figures contain alphamaps, which are m-by-1 arrays of alpha values.

See the following sections for more information on color:

- "Specifying Patch Coloring" on page 5-14 in Creating 3-D Models with Patches in the Using MATLAB Graphics documentation
- "Coloring Mesh and Surface Plots" on page 1-14 in Creating 3-D Graphs in the Using MATLAB Graphics documentation

Transparency Properties

The following table summarizes the object properties that control transparency.

Property	Purpose
AlphaData	Transparency data for image and surface objects
AlphaDataMapping	Transparency data mapping method
FaceAlpha	Transparency of the faces (patch and surface only)
EdgeAlpha	Transparency of the edges (patch and surface only)
FaceVertexAlphaData	Patch only alpha data property
ALim	Alpha axis limits
ALimMode	Alpha axis limits mode
Alphamap	Figure alphamap

Transparency Functions

There are three functions that simplify the process of setting alpha properties.

Function	Purpose
alpha	Set or query transparency properties for objects in current axes
alphamap	Specify the figure alphamap
alim	Set or query the axes alpha limits


Specifying a Single Transparency Value

Specifying a single transparency value for graphics objects is useful when you want to reveal structure that is obscured with opaque objects. For patches and surfaces, use the FaceAlpha and EdgeAlpha properties to specify the transparency of faces and edges. The following example illustrates this.

Example – Transparent Isosurface


This example uses the flow function to generate data for the speed profile of a submerged jet within an infinite tank. One way to visualize this data is by creating an isosurface illustrating where the rate of flow is equal to a specified value.

```
[x y z v] = flow;
p = patch(isosurface(x,y,z,v,-3));
isonormals(x,y,z,v,p);
set(p,'facecolor','red','edgecolor','none');
daspect([1 1 1]);
view(3); axis tight; grid on;
camlight; lighting gouraud;
```



Adding transparency to the isosurface reveals that there is greater complexity in the fluid flow than is visible using the opaque surface. The statement alpha(.5)

sets the FaceAlpha value for the isosurface face to .5.



Setting a Single Transparency Value for Images

For images, the statement

alpha(.5)

sets AlphaData to .5. When the AlphaDataMapping property is set to none (the default), setting AlphaData on an image causes the entire image to be rendered with the specified alpha value.

Mapping Data to Transparency – Alpha Data

- "Size of the Alpha Data Array" on page 4-9
- "Mapping Alpha Data to the Alphamap" on page 4-9
- "Example Mapping Data to Color or Transparency" on page 4-10

Alpha data is analogous to color data (e.g., the CData property of surfaces). When you create a surface, MATLAB maps each element in the color data array to a color in the colormap. Similarly, each element in the alpha data maps to a transparency value in the alphamap.

Specify surface and image alpha data with the AlphaData property. For patch objects, use the FaceVertexAlphaData property.

You can control how MATLAB interprets alpha data with the following properties:

- FaceAlpha and EdgeAlpha Enable you to select flat or interpolated transparency rendering. If set to a single transparency value, MATLAB applies this value to all faces or edges and does not use the alpha data.
- AlphaDataMapping and ALim Determine how MATLAB maps the alpha data to the alphamap. By default, MATLAB scales the alpha data to be within the range [0 1].
- Alphamap Contains the actual transparency values to which the data is to be mapped.

Note that there are differences between the default values of equivalent color and alpha properties because, in contrast to color, transparency is not displayed by default. The following table highlights these differences.

Color Property	Default	Alpha Property	Default
FaceColor	Flat	FaceAlpha	1 (opaque)
CData	Equal to ZData	AlphaData and FaceVertexAlphaData	1 (scalar)

By default, objects have single-valued alpha data. Therefore you cannot specify flat or interp FaceAlpha or EdgeAlpha without first setting AlphaData to an array of the appropriate size.

The sections that follow illustrate how to use these properties to display object data as degrees of transparency.

Size of the Alpha Data Array

In order to use nonscalar alpha data, you need to specify the alpha data as an array equal in size to

- CData of images and surfaces
- The number of faces (flat) or the number of vertices (interpolated) defined in the FaceVertexAlphaData property of patches

Once you have specified an alpha data array of the proper size, you can select the face and edge rendering you want to use. Flat uses one transparency value per face, while interpolated performs bilinear interpolation of the values at each vertex.

Mapping Alpha Data to the Alphamap

You can control how MATLAB maps the alpha data to the alphamap using the AlphaDataMapping property. There are three possible mappings:


- none Interpret the values in alpha data as transparency values (data values must be between 0 and 1, or will be clamped to 0 or 1). This is the default mapping.
- scaled Transform the alpha data to span the portion of the alphamap indicated by the axes ALim property, linearly mapping data values to alpha values. This is the same way color data is mapped to the colormap.
- direct Use the alpha data directly as indices into the figure alphamap.

By default, objects have scalar alpha data (AlphaData and FaceVertexAlphaData) set to the value 1.

Example – Mapping Data to Color or Transparency


This example displays a surface plot of a function of two variables. The color is mapped to the gradient of the z data.

```
[x,y] = meshgrid([-2:.2:2]);
z = x.*exp(-x.^2-y.^2);
surf(x,y,z,gradient(z)); axis tight
```



You can map transparency to the gradient of z in a similar way.

```
surf(x,y,z,'FaceAlpha','flat',...
'AlphaDataMapping','scaled',...
'AlphaData',gradient(z),...
'FaceColor','blue');
axis tight
```



Selecting an Alphamap

An alphamap is simply an array of values ranging from 0 to 1. The size of the array can be either m-by-1 or 1-by-m.

The default alphamap contains 64 values ranging linearly from 0 to 1, as you can see in the following plot.

```
Default Alphamap
 1
0.9
0.8
0.7
0.6
0.5
0.4
0.3
0.2
0.1
 0
                                                   70
                20
                       30
                              40
                                     50
   0
         10
                                            60
```


plot(get(gcf, 'Alphamap'))

This alphamap displays the lowest alpha data values as completely transparent and the highest alpha data values as opaque.

The alphamap function creates some useful predefined alphamaps and also enables you to modify existing maps. For example,

```
plot(alphamap('vup'))
```

produces the following alphamap.




You can shift the values using the increase or decrease options. For example,

```
alphamap('increase',.4)
```

adds the value .4 to all values in the current figure's alphamap. Replotting the 'vup' alphamap illustrates the change. Note how the values are clamped to the range $[0\ 1]$.

```
plot(get(gcf, 'Alphamap'))
```



Example – Modifying the Alphamap

This example uses slice planes to examine volume data. The slice planes use the color data for alpha data and employ a rampdown alphamap (the values range from 1 to 0):

1 Create the volume data by evaluating a function of three variables.

```
[x,y,z] = meshgrid(-1.25:.1:-.25,-2:.2:2,-2:.1:2);
v = x.*exp(-x.^2-y.^2-z.^2);
```

2 Create the slice planes, set the alpha data equal to the color data, and specify interpolated FaceAlpha.


```
h = slice(x,y,z,v,[-1 -.75 -.5],[],[0]);
alpha('color')
set(h,'EdgeColor','none','FaceColor','interp',...
'FaceAlpha','interp')
```

3 Install the rampdown alphamap and increase each value in the alphamap by .1 to achieve the desired degree of transparency. Specify the hsv colormap.

```
alphamap('rampdown')
```

```
alphamap('increase',.1)
colormap(hsv)
```

This alphamap causes the smallest values of the function (around zero) to be displayed with the least transparency and the greatest values to display with the most transparency. This enables you to see through the slice planes, while at the same time preserving the data around zero.



Creating 3-D Models with Patches

Introduction to Patch Objects (p. 5-2)	Overview of what a patch object is and how to define one
Multifaceted Patches (p. 5-7)	Shows how to define a 3-D patch object using both x-, y-, and z-coordinate and faces/vertices data, and illustrates flat and interpolated face coloring
Specifying Patch Coloring (p. 5-14)	How to specify patch coloring using various patch properties
Patch Edge Coloring (p. 5-16)	Details about how MATLAB determines patch edge coloring
Interpreting Indexed and Truecolor Data (p. 5-19)	Specifying color data that uses colormaps or defines explicit colors

Introduction to Patch Objects

- "Defining Patches" on page 5-2
- "Behavior of the patch Function" on page 5-3
- "Creating a Single Polygon" on page 5-4

A patch graphics object is composed of one or more polygons that may or may not be connected. Patches are useful for modeling real-world objects such as airplanes or automobiles, and for drawing 2- or 3-D polygons of arbitrary shape.

In contrast, surface objects are rectangular grids of quadrilaterals and are better suited for displaying planar topographies such as the values of mathematical functions of two variables, the contours of data in a rectangular plane, or parameterized surfaces such as spheres.

A number of MATLAB functions create patch objects — fill, fill3, isosurface, isocaps, some of the contour functions, and patch. This section concentrates on use of the patch function.

Defining Patches

You define a patch by specifying the coordinates of its vertices and some form of color data. Patches support a variety of coloring options that are useful for visualizing data superimposed on geometric shapes.

There are two ways to specify a patch:

- By specifying the coordinates of the vertices of each polygon, which MATLAB connects to form the patch
- By specifying the coordinates of each *unique* vertex and a matrix that specifies how to connect these vertices to form the faces

The second technique is preferred for multifaceted patches because it generally requires less data to define the patch; vertices shared by more than one face need be defined only once. This section provides examples of both techniques.

Behavior of the patch Function

There are two forms of the patch function -- high-level syntax and low-level syntax. The behavior of the patch function differs somewhat depending on which syntax you use.

High-Level Syntax

When you use the high-level syntax, MATLAB automatically determines how to color each face based on the color data you specify. The high-level syntax enables you to omit the property names for the x-, y-, and z-coordinates and the color data, as long as you specify these arguments in the correct order.

```
patch(x-coordinates,y-coordinates,z-coordinates,colordata)
```

However, you must specify color data so MATLAB can determine what type of coloring to use. If you do not specify color data, MATLAB returns an error.

```
patch(sin(t),cos(t))
??? Error using ==> patch
Not enough input arguments.
```

Low-Level Syntax

The low-level syntax accepts only property name/property value pairs as arguments and does not automatically color the faces unless you also change the value of the FaceColor property. For example, the statement

```
patch('XData',sin(t),'YData',cos(t)) % Low-level syntax
```

draws a patch with white face color because the factory default value for the FaceColor property is the color white.

See the list of patch properties in the MATLAB Function Reference and the get command for information on how to obtain the factory and user default values for properties.

Interpreting the Color Argument

When you use the low-level syntax, MATLAB interprets the third (or fourth if there are *z*-coordinates) argument as color data. If you intend to define a patch with *x*-, *y*-, and *z*-coordinates, but leave out the color, MATLAB interprets the *z*-coordinates as color data, and then draws a 2-D patch. For example,

h = patch(sin(t), cos(t), 1:length(t))

draws a patch with all vertices at z = 0, colored by interpolating the vertex colors (since there is one color for each vertex), whereas

```
h = patch(sin(t), cos(t), 1:length(t), 'y')
```

draws a patch with vertices at increasing values of z, colored yellow.

"Specifying Patch Coloring" on page 5-14 provides more information on options for coloring patches.


Creating a Single Polygon

A polygon is simply a patch with one face. To create a polygon, specify the coordinates of the vertices and color data with a statement of the form

```
patch(x-coordinates,y-coordinates,[z-coordinates],colordata)
```

For example, these statements display a 10-sided polygon with a yellow face enclosed by a black edge. The axis equal command produces a correctly proportioned polygon.

```
t = 0:pi/5:2*pi;
patch(sin(t),cos(t),'y')
axis equal
```




The first and last vertices need not coincide; MATLAB automatically closes each polygonal face of the patch. In fact, it is generally better to define each vertex only once, particularly if you are using interpolated face coloring.

Interpolated Face Colors

You can control many aspects of the patch coloring. For example, instead of specifying a single color, you can provide a range of numerical values that map the color at each vertex to a color in the figure colormap.

```
a = t(1:length(t)-1); %remove redundant vertex definition
patch(sin(a),cos(a),1:length(a),'FaceColor','interp')
colormap cool;
axis equal
```



MATLAB now interpolates the colors across the face of the patch. You can color the edges of the patch the same way, by setting the edge colors to be interpolated. The command is

patch(sin(t),cos(t),1:length(t),'EdgeColor','interp')

"Specifying Patch Coloring" on page 5-14 provides more information on options for coloring patches.

Multifaceted Patches


- "Example Defining a Cube" on page 5-7
- "Modifying Patch Data" on page 5-10

If you specify the *x*-, *y*-, and *z*-coordinate arguments as vectors, MATLAB draws a single polygon by connecting the points. If the arguments are matrices, MATLAB draws one polygon per column, producing a single patch with multiple faces. These faces need not be connected and can be self-intersecting.

Alternatively, you can specify the coordinates of each unique vertex and the order in which to connect them to form the faces. The examples in this section illustrate both techniques.


Example – Defining a Cube

A cube is defined by eight vertices that form six sides. This illustration shows the coordinates of the vertices defining a cube in which the sides are one unit in length.



Specifying X, Y, and Z Coordinates


Each of the six faces has four vertices. Because you do not need to close each polygon (i.e., the first and last vertices do not need to be the same), you can define this cube using a 4-by-6 matrix for each of the *x*-, *y*-, and *z*-coordinates.



Each column of the matrices specifies a different face. Note that while there are only eight vertices, you must specify 24 vertices to define all six faces. Since each face shares vertices with four other faces, you can define the patch more efficiently by defining each vertex only once and then specifying the order in which to connect these vertices to form each face. The patch Vertices and Faces properties define patches in just this way.

Specifying Faces and Vertices

These matrices specify the cube using Vertices and Faces.



Using the vertices/faces technique can save a considerable amount of computer memory when patches contain a large number of faces. This technique requires the formal patch function syntax, which entails assigning values to the Vertices and Faces properties explicitly. For example,

```
patch('Vertices',vertex_matrix,'Faces',faces_matrix)
```

Because the high-level syntax does not automatically assign face or edge colors, you must set the appropriate properties to produce patches with colors other than the default white face color and black edge color.

Flat Face Color

Flat face color is the result of specifying one color per face. For example, using the vertices/faces technique and the FaceVertexCData property to define color, this statement specifies one color per face and sets the FaceColor property to flat.

```
patch('Vertices',vertex_matrix,'Faces',faces_matrix,...
'FaceVertexCData',hsv(6),'FaceColor','flat')
```

Because truecolor specified with the FaceVertexCData property has the same format as a MATLAB colormap (i.e., an *n*-by-3 array of RGB values), this example uses the hsv colormap to generate the six colors required for flat shading.

Interpolated Face Color

Interpolated face color means the vertex colors of each face define a transition of color from one vertex to the next. To interpolate the colors between vertices, you must specify a color for each vertex and set the FaceColor property to interp.

```
patch('Vertices',vertex_matrix,'Faces',faces_matrix,...
'FaceVertexCData',hsv(8),'FaceColor','interp')
```


Changing to the standard 3-D view and making the axis square,

view(3); axis square

produces a cube with each face colored by interpolating the vertex colors.

To specify the same coloring using the x, y, z, c technique, c must be an m-by-n-by-3 array, where the dimensions of x, y, and z are m-by-n.

This diagram shows the correspondence between the FaceVertexCData and CData properties.



"Specifying Patch Coloring" on page 5-14 discusses coloring techniques in more detail.

Modifying Patch Data

In general, if you define a patch with Faces and Vertices data and then want to modify its data, you should continue to use these same properties. Do not switch modes and modify the XData, YData, ZData, or CDataproperties.

How to Handle Mixed Data


When you create a patch specified with Faces and Vertices data, MATLAB constructs arrays of data for the XData, YData, ZData and CData properties when you query them. However, these arrays contain only enough data to define the same number of vertices as there are referred to in the Faces property. If the number of vertices in the Vertices property is greater than the number of vertices used by the Faces property, then MATLAB cannot generate complete x, y, and z data from the faces and vertex data.

While it is better to avoid mixing how you specify data when defining patches directly, you might need to modify patch data when using functions that themselves create patch objects. For example, the bar function creates patch objects to implement the bars in a graph.

Note The barseries YData property enables you to modify the bar graph without the need to use the following steps. See the bar function for more information on working with bar graphs.

The function uses y-data values to determine the height of each bar, but creates each bar as the face of a patch specified by faces and vertices. For example,

```
rand('state',4)
h = bar(rand(10,1)); % y data for each bar
p = get(h,'children'); % get the handle of the patch
cl = get(gca,'CLim');
```



Before you can change the patch YData property, you must switch the patch to x, y, and z data as follows:

```
xd = get(p,'XData');
yd = get(p,'YData');
zd = get(p,'ZData');
cd = get(p,'CData');
set(p,'XData',xd,'YData',yd,'ZData',zd,'CData',cd);
set(gca,'CLim',cl)
```

This setting of the XData, YData, ZData and CData properties causes the patch function to match the faces and vertex data with x, y, and z data. Note that because there is a change in the patch data, the color limits change, so you must use the original values for the axes CLim property.

You can now modify the y data values to change your graph. For example, the value of bar at x = 10 is 0.0122:

```
yd(:,10)
ans =
```

0


0.0122 0.0122 0

You can change this bar by changes rows 2 and 3:

yd(2:3,10) = [.65 .65];

Now reset the patch YData property:

set(p,'YData',yd)



Another reason you might want to modify face-vertex data for bar graphs or other objects is to modify their CData to customize how they are colored. Techniques for doing this for 2–D and 3–D bar graphs are explained in "Coloring 2-D Bars According to Height" and "Coloring 3-D Bars According to Height" in the MATLAB Graphics documentation.

Specifying Patch Coloring

Patch coloring is defined differently from surface object coloring in that patches do not automatically generate color data based on the value of the z-coordinate at each vertex. You must explicitly specify patch coloring, or MATLAB uses the default white face color and black edge color.

You can specify patch face coloring by defining

- A single color for all faces
- One color for each face, which is used for flat coloring
- One color for each vertex, which is used for interpolated coloring

Specify the face color using either the CData property, if you are using x-, y-, and z-coordinates, or the FaceVertexCData property, if you are specifying vertices and faces.

Patch Color Properties

This table summarizes the patch properties that control color (exclusive of those used when light sources are present).

Property	Purpose
CData	Specify single, per face, or per vertex colors in conjunction with x, y, and z data
CDataMapping	Specifies whether color data is scaled or used directly as indices into the figure colormap
FaceVertexCData	Specify single, per face, or per vertex colors in conjunction with faces and vertices data
EdgeColor	Specifies whether edges are invisible, a single color, a flat color determined by vertex colors, or interpolated colors determined by vertex colors
FaceColor	Specifies whether faces are invisible, a single color, a flat color determined by vertex colors, or interpolated colors determined by vertex colors

Property	Purpose
MarkerEdgeColor	Specifies the color of the marker, or the edge color for filled markers
MarkerFaceColor	Specifies the fill color for markers that are closed shapes

Patch Edge Coloring

- "Example Specifying Flat Edge and Face Coloring" on page 5-16
- "Coloring Edges with Shared Vertices" on page 5-17

Each patch face has a bounding edge, which you can color as

- A single color for all edges
- A flat color defined by the color of the vertex that precedes the edge
- Interpolated colors determined by the two vertices that bound the edge


Note that patch edge colors can be flat or interpolated only when you specify a color for each vertex. For flat edge coloring, MATLAB uses the color of the vertex preceding the edge to determine the color of the edge. The order in which you specify the vertices establishes which vertex colors a particular edge.

The following examples illustrate patch edge coloring:

- "Example Specifying Flat Edge and Face Coloring" on page 5-16
- "Coloring Edges with Shared Vertices" on page 5-17

Example – Specifying Flat Edge and Face Coloring


These statements create a square patch.



The Faces property value, [1 2 3 4], determines the order in which MATLAB connects the vertices. In this case, the order is red, green, magenta, and yellow. If you change this order, the results can be quite different. For example, specifying the Faces property as

f = [4 3 2 1];

changes the order to yellow, magenta, green, and red. Note that changing the order not only changes the color of the edges, but also the color of the face, which is the color of the first vertex specified.




Coloring Edges with Shared Vertices

Each patch face is bound by edges, which are line segments that connect the vertices. When patches have multiple faces that share vertices, some of the

edges might overlap. In such cases, the edges of the most recently drawn face overlie previously drawn edges.

For example, this illustration shows a patch with four faces and flat colored edges (FaceColor set to none, EdgeColor set to flat).



The arrows indicate the order in which each edge is drawn in the first, second, third, and fourth face. The color at each vertex determines the color of the edge that follows it. Notice how the second edge in the first face would be green except that the second face drew its fourth edge from the magenta vertex. You can see similar effects in all shared edges.

For EdgeColor set to interp, MATLAB interpolates colors between adjacent vertices. In this case, the order in which you specify the vertices does not affect the edge color.

Interpreting Indexed and Truecolor Data

- "Indexed Color Data" on page 5-19
- "Truecolor Patches" on page 5-22
- "Interpolating in Indexed Color Versus Truecolor" on page 5-22

MATLAB interprets the patch color data in one of two ways:

- Indexed color data Numerical values that are mapped to colors defined in the figure colormap
- Truecolor data RGB triples that define colors explicitly and do not make use of the figure colormap

The dimensions of the color data (CData or FaceVertexCData) determine how MATLAB interprets it. If you specify only one numeric value per patch, per face, or per vertex, then MATLAB interprets the data as indexed. If there are three numeric values per patch, face, or vertex, then MATLAB interprets the data as RGB values.

Indexed Color Data

MATLAB interprets indexed color data as either values to scale before mapping to the colormap, or directly as indices into the colormap. You control the interpretation by setting the CDataMapping property. The default is to scale the data.

Scaled Color


By default, MATLAB scales the color data so that the minimum value maps to the first color in the colormap, the maximum value maps to the last color in the colormap, and values in between are linearly transformed to span the colormap. This enables you to use colormaps of different sizes without changing your data and to use data in any range of values without changing the colormap.

For example, the following patch has eight triangular faces with a total of 24 (nonunique) vertices. The color data are integers that range from one to 24, but could be any values.

The variable c contains the color data. It is a 3-by-8 matrix, with each column specifying the colors for the three vertices of each face.

с =								
	1	4	7	10	13	16	19	22
	2	5	8	11	14	17	20	23
	3	6	9	12	15	18	21	24

The color bar (colorbar) on the right side of the patch illustrates the colormap used and indicates with the vertical axis which color is mapped to the respective data value.



You can alter the mapping of color data to colormap entry using the caxis command. This command uses a two-element vector [cmin cmax] to specify what data values map to the beginning and end of the colormap, thereby shifting the color mapping.

By default, MATLAB sets cmin to the minimum value and cmax to the maximum value of the color data of all graphics objects within the axes. However, you can set these limits to span any range of values and thereby shift the color mapping. See Calculating Color Limits in "Axes Properties" in the Using MATLAB Graphics documentation for more information.

The color data does not need to be a sequential list of integers; it can be any matrix with dimensions matching the coordinate data. For example,

```
patch(x,y,z,rand(size(z)))
```


Direct Color

If you set the patch CDataMapping property to direct,

```
set(patch_handle, 'CDataMapping', 'direct')
```

MATLAB interprets each color data value as a direct index into the colormap. That is, a value of 1 maps to the first color, a value of 2 maps to the second color, and so on.

The patch from the previous example would then use only the first 24 colors in the colormap.



This example uses integer color data. However, if the values are not integers, MATLAB converts them according to these rules:

- If value is < 1, it maps to the first color in the colormap.
- If value is not an integer, it is rounded to the nearest integer toward zero.
- If value > length(colormap), it maps to the last color in the colormap.

Unscaled color data is more commonly used for images where there is typically a colormap associated with a particular image.

Truecolor Patches

Truecolor is a means to specify a color explicitly with RGB values rather than pointing to an entry in the figure colormap. Truecolor generally provides a greater range of colors than can be defined in a colormap.


Using truecolor eliminates the mapping of data to colormap entries. On the other hand, you cannot change the coloring of the patch without redefining the color data (as opposed to just changing the colormap).

Interpolating in Indexed Color Versus Truecolor

When you specify interpolated face coloring, MATLAB determines the color of each face by interpolating the vertex colors. The method of interpolation depends on whether you specified truecolor data or indexed color data.

With truecolor data, MATLAB interpolates the numeric RGB values defined for the vertices. This generally produces a smooth variation of color across the face. In contrast, indexed color interpolation uses only colors that are defined in the colormap. With certain colormaps, the results can be quite different.

To illustrate this difference, these two patches are defined with the same vertex colors. Circular markers indicate the yellow, red, and blue vertex colors.



The patch on the left uses indexed colors obtained from the six-element colormap shown next to it. The color data maps the vertex colors to the colormap elements indicated in the picture. With this colormap, interpolating from the cyan vertex to the blue vertex can include only the colors green, red, yellow, and magenta, hence the banding.

Interpolation in RGB space makes no use of the colormap. It is simply the gradual transition from one numeric value to another. For example, interpolating from the cyan vertex to the blue vertex follows a progression similar to these values.

0 1 1, 0 0.9 1, 0 0.8 1, ... 0 0.2 1, 0 0.1 1, 0 0 1

In reality each pixel would be a different color so the incremental change would be much smaller than illustrated here.

6

Volume Visualization Techniques

Overview of Volume Visualization (p. 6-3)	Volume data visualization with MATLAB, including examples of available techniques
Volume Visualization Functions (p. 6-5)	Functions used for volume visualization
Visualizing Scalar Volume Data (p. 6-7)	Techniques available for visualizing scalar volume data
Visualizing MRI Data (p. 6-8)	Visualizing MRI data using 2- and 3-D contour slices, isosurfaces, isocaps, and lighting
Exploring Volumes with Slice Planes (p. 6-14)	Using slice planes to scan the interior of scalar volumes
Connecting Equal Values with Isosurfaces (p. 6-19)	Using isosurfaces to illustrate scalar fluid-flow data
Isocaps Add Context to Visualizations (p. 6-21)	Using isocaps to improve the shape definition of isosurface plots
Visualizing Vector Volume Data (p. 6-26)	Techniques for visualizing vector volume data, including scalar techniques, determining starting points for stream plots, and plotting subregions of volumes
Stream Line Plots of Vector Data (p. 6-32)	Using stream lines, slice planes, and contour lines in one graph

Displaying Curl with Stream Ribbons (p. 6-35)	Example using stream ribbon plots to display the curl of a vector field
Displaying Divergence with Stream Tubes (p. 6-38)	Example using stream tube plots to display the divergence of a vector field. Slice planes and contour lines enhance the visualization.
Creating Stream Particle Animations (p. 6-41)	Example using stream lines and stream particles to create an animation illustrating wind currents
Vector Field Displayed with Cone Plots (p. 6-44)	Example using cone plots, isosurfaces, lighting, and camera placement to visualize a vector field

Overview of Volume Visualization

- "Examples of Volume Data" on page 6-3
- "Selecting Visualization Techniques" on page 6-4
- "Steps to Create a Volume Visualization" on page 6-4

Volume visualization is the creation of graphical representations of data sets that are defined on three-dimensional grids. Volume data sets are characterized by multidimensional arrays of scalar or vector data. These data are typically defined on lattice structures representing values sampled in 3-D space. There are two basic types of volume data:

- Scalar volume data contains single values for each point.
- *Vector volume data* contains two or three values for each point, defining the components of a vector.

Examples of Volume Data

An example of scalar volume data is that produced by the flow M-file. The flow data represents the speed profile of a submerged jet within an infinite tank. Typing

[x,y,z,v] = flow;

produces four 3-D arrays. The x, y, and z arrays specify the coordinates of the scalar values in the array v.

The wind data set is an example of vector volume data that represents air currents over North America. You can load this data in the MATLAB workspace with the command

load wind

This data set comprises six 3-D arrays: x, y, and z are the coordinate data for the arrays u, v, and w, which are the vector components for each point in the volume.

Selecting Visualization Techniques

The techniques you select to visualize volume data depend on what type of data you have and what you want to learn. In general,

- Scalar data is best viewed with isosurfaces, slice planes, and contour slices.
- Vector data represents both a magnitude and direction at each point, which is best displayed by stream lines (particles, ribbons, and tubes), cone plots, and arrow plots. Most visualizations, however, employ a combination of techniques to best reveal the content of the data.

The material in these sections describes how to apply a variety of techniques to typical volume data.

Steps to Create a Volume Visualization

Creating an effective visualization requires a number of steps to compose the final scene. These steps fall into four basic categories:

- **1** Determine the characteristics of your data. Graphing volume data usually requires knowledge of the range of both the coordinates and the data values.
- **2** Select an appropriate plotting routine. The information in this section helps you select the right methods.
- **3** Define the view. The information conveyed by a complex three-dimensional graph can be greatly enhanced through careful composition of the scene. Viewing techniques include adjusting camera position, specifying aspect ratio and project type, zooming in or out, and so on.
- **4** Add lighting and specify coloring. Lighting is an effective means to enhance the visibility of surface shape and to provide a three-dimensional perspective to volume graphs. Color can convey data values, both constant and varying.

Volume Visualization Functions

- "Functions for Scalar Data " on page 6-5
- "Functions for Vector Data" on page 6-6

MATLAB provides functions that enable you to apply a variety of volume visualization techniques. The following tables group these functions into two categories based on the type of data (scalar or vector) that each is designed to work with. The reference page for each function provides examples of the intended use.

Function	Purpose
contourslice	Draw contours in volume slice planes
isocaps	Compute isosurface end-cap geometry
isocolors	Compute the colors of isosurface vertices
isonormals	Compute normals of isosurface vertices
isosurface	Extract isosurface data from volume data
patch	Create a patch (multipolygon) graphics object
reducepatch	Reduce the number of patch faces
reducevolume	Reduce the number of elements in a volume data set
shrinkfaces	Reduce the size of each patch face
slice	Draw slice planes in volume
smooth3	Smooth 3-D data
surf2patch	Convert surface data to patch data
subvolume	Extract subset of volume data set

Functions for Scalar Data

Function	Purpose
coneplot	Plot velocity vectors as cones in 3-D vector fields
curl	Compute the curl and angular velocity of a 3-D vector field
divergence	Compute the divergence of a 3-D vector field
interpstreamspeed	Interpolate streamline vertices from vector-field magnitudes
streamline	Draw stream lines from 2-D or 3-D vector data
streamparticles	Draw stream particles from vector volume data
streamribbon	Draw stream ribbons from vector volume data
streamslice	Draw well-spaced stream lines from vector volume data
streamtube	Draw stream tubes from vector volume data
stream2	Compute 2-D stream line data
stream3	Compute 3-D stream line data
volumebounds	Return coordinate and color limits for volume (scalar and vector)

Visualizing Scalar Volume Data

Typical scalar volume data is composed of a 3-D array of data and three coordinate arrays of the same dimensions. The coordinate arrays specify the *x*-, *y*-, and *z*-coordinates for each data point.

The units of the coordinates depend on the type of data. For example, flow data might have coordinate units of inches and data units of psi.

Techniques for Visualizing Scalar Data

MATLAB supports a number of functions that are useful for visualizing scalar data:

- Slice planes provide a way to explore the distribution of data values within the volume by mapping values to colors. You can orient slice planes at arbitrary angles, as well as use nonplanar slices. (For illustrations of how to use slice planes, see slice, a volume slicing example, and slice planes used to show context.) You can specify the data used to color isosurfaces, enabling you to display different information in color and surface shape (see isocolors).
- Contour slices are contour plots drawn at specific coordinates within the volume. Contour plots enable you to see where in a given plane the data values are equal. See contourslice for an example
- Isosurfaces are surfaces constructed by using points of equal value as the vertices of patch graphics objects.

Visualizing MRI Data

An example of scalar data includes Magnetic Resonance Imaging (MRI) data. This data typically contains a number of slice planes taken through a volume, such as the human body. MATLAB includes an MRI data set that contains 27 image slices of a human head. This section describes some useful techniques for visualizing MRI data.

Example – Ways to Display MRI Data

This example illustrate the following techniques applied to MRI data:

- A series of 2-D images representing slices through the head
- 2-D and 3-D contour slices taken at arbitrary locations within the data
- An isosurface with isocaps showing a cross section of the interior

Changing the Data Format

The MRI data, D, is stored as a 128-by-128-by-1-by-27 array. The third array dimension is used typically for the image color data. However, since these are indexed images (a colormap, map, is also loaded) there is no information in the third dimension, which you can remove using the squeeze command. The result is a 128-by-128-by-27 array.


The first step is to load the data and transform the data array from 4-D to 3-D.

load mri
D = squeeze(D);

Displaying Images of MRI Data

To display one of the MRI images, use the image command, indexing into the data array to obtain the eighth image. Then adjust axis scaling, and install the MRI colormap, which was loaded along with the data.

```
image_num = 8;
image(D(:,:,image_num))
axis image
colormap(map)
```



Save the *x*- and *y*-axis limits for use in the next part of the example.

x = xlim; y = ylim;


Displaying a 2-D Contour Slice

You can treat this MRI data as a volume because it is a collection of slices taken progressively through the 3-D object. Use contourslice to display a contour plot of a slice of the volume. To create a contour plot with the same orientation and size as the image created in the first part of this example, adjust the y-axis direction (axis), set the limits (xlim, ylim), and set the data aspect ratio (daspect).

```
contourslice(D,[],[],image_num)
axis ij
xlim(x)
ylim(y)
daspect([1,1,1])
```

colormap('default')


This contour plot uses the figure colormap to map color to contour value.



Displaying 3-D Contour Slices

Unlike images, which are 2-D objects, contour slices are 3-D objects that you can display in any orientation. For example, you can display four contour slices in a 3-D view. To improve the visibility of the contour line, increase the LineWidth to 2 points (one point equals 1/72 of an inch).

```
phandles = contourslice(D,[],[],[1,12,19,27],8);
view(3); axis tight
set(phandles, 'LineWidth',2)
```



Displaying an Isosurface

You can use isosurfaces to display the overall structure of a volume. When combined with isocaps, this technique can reveal information about data on the interior of the isosurface.

First, smooth the data with smooth3; then use isosurface to calculate the isodata. Use patch to display this data as a graphics object.

```
Ds = smooth3(D);
hiso = patch(isosurface(Ds,5),...
'FaceColor',[1,.75,.65],...
'EdgeColor','none');
```

Adding an Isocap to Show a Cutaway Surface

Use isocaps to calculate the data for another patch that is displayed at the same isovalue (5) as the surface. Use the unsmoothed data (D) to show details of the interior. You can see this as the sliced-away top of the head.

```
hcap = patch(isocaps(D,5),...
'FaceColor','interp',...
'EdgeColor','none');
```

colormap(map)

Defining the View


Define the view and set the aspect ratio (view, axis, daspect).

```
view(45,30)
axis tight
daspect([1,1,.4])
```

Add Lighting

Add lighting and recalculate the surface normals based on the gradient of the volume data, which produces smoother lighting (camlight, lighting, isonormals). Increase the AmbientStrength property of the isocap to brighten the coloring without affecting the isosurface. Set the SpecularColorReflectance of the isosurface to make the color of the specular reflected light closer to the color of the isosurface; then set the SpecularExponent to reduce the size of the specular spot.

```
lightangle(45,30);
set(gcf,'Renderer','zbuffer'); lighting phong
isonormals(Ds,hiso)
set(hcap,'AmbientStrength',.6)
set(hiso,'SpecularColorReflectance',0,'SpecularExponent',50)
```



Example of an Isocap

The isocap uses interpolated face coloring, which means the figure colormap determines the coloring of the patch. This example uses the colormap supplied with the data.

To display isocaps at other data values, try changing the isosurface value or use the subvolume command. See the isocaps and subvolume reference pages for examples.

Exploring Volumes with Slice Planes

- "Example Slicing Fluid Flow Data" on page 6-14
- "Modifying the Color Mapping" on page 6-17

A slice plane (which does not have to be planar) is a surface that takes on coloring based on the values of the volume data in the region where the slice is positioned. Slice planes are useful for probing volume data sets to discover where interesting regions exist, which you can then visualize with other types of graphs (see the slice example). Slice planes are also useful for adding a visual context to the bound of the volume when other graphing methods are also used (see coneplot and "Stream Line Plots of Vector Data" on page 6-32 for examples).

Use the slice function to create slice planes.

Example – Slicing Fluid Flow Data

This example slices through a volume generated by the flow M-file.

1. Investigate the Data

Generate the volume data with the command

[x,y,z,v] = flow;

Determine the range of the volume by finding the minimum and maximum of the coordinate data.

```
xmin = min(x(:));
ymin = min(y(:));
zmin = min(z(:));
xmax = max(x(:));
ymax = max(y(:));
zmax = max(z(:));
```

2. Create a Slice Plane at an Angle to the X-Axes

To create a slice plane that does not lie in an axes plane, first define a surface and rotate it to the desired orientation. This example uses a surface that has the same x- and y- coordinates as the volume.

```
hslice = surf(linspace(xmin,xmax,100),...
linspace(ymin,ymax,100),...
zeros(100));
```

Rotate the surface by -45 degrees about the *x*-axis and save the surface XData, YData, and ZData to define the slice plane; then delete the surface.

```
rotate(hslice,[-1,0,0],-45)
xd = get(hslice,'XData');
yd = get(hslice,'YData');
zd = get(hslice,'ZData');
delete(hslice)
```

3. Draw the Slice Planes

Draw the rotated slice plane, setting the FaceColor to interp so that it is colored by the figure colormap, and set the EdgeColor to none. Increase the DiffuseStrength to .8 to make this plane shine more brightly after adding a light source.

```
h = slice(x,y,z,v,xd,yd,zd);
set(h,'FaceColor','interp',...
'EdgeColor','none',...
'DiffuseStrength',.8)
```

Set hold to on and add three more orthogonal slice planes at xmax, ymax, and zmin to provide a context for the first plane, which slices through the volume at an angle.

```
hold on
hx = slice(x,y,z,v,xmax,[],[]);
set(hx,'FaceColor','interp','EdgeColor','none')
hy = slice(x,y,z,v,[],ymax,[]);
set(hy,'FaceColor','interp','EdgeColor','none')
```

```
hz = slice(x,y,z,v,[],[],zmin);
set(hz,'FaceColor','interp','EdgeColor','none')
```

4. Define the View

To display the volume in correct proportions, set the data aspect ratio to [1,1,1] (daspect). Adjust the axis to fit tightly around the volume (axis) and turn on the box to provide a sense of a 3-D object. The orientation of the axes can be selected initially using rotate3d to determine the best view.


Zooming in on the scene provides a larger view of the volume (camzoom). Selecting a projection type of perspective gives the rectangular solid more natural proportions than the default orthographic projection (camproj).

```
daspect([1,1,1])
axis tight
box on
view(-38.5,16)
camzoom(1.4)
camproj perspective
```

5. Add Lighting and Specify Colors

Adding a light to the scene makes the boundaries between the four slice planes more obvious because each plane forms a different angle with the light source (lightangle). Selecting a colormap with only 24 colors (the default is 64) creates visible gradations that help indicate the variation within the volume.

```
lightangle(-45,45)
colormap (jet(24))
set(gcf,'Renderer','zbuffer')
```



The "Modifying the Color Mapping" on page 6-17 section shows how to modify how the data is mapped to color.

Modifying the Color Mapping

The current colormap determines the coloring of the slice planes. This enables you to change the slice plane coloring by

- Changing the colormap
- Changing the mapping of data value to color

Suppose, for example, you are interested in data values only between -5 and 2.5 and would like to use a colormap that mapped lower values to reds and higher values to blues (that is, the opposite of the default jet colormap).

Customizing the Colormap

The first step is to flip the colormap (colormap, flipud).

```
colormap (flipud(jet(24)))
```


Adjusting the Color Limits

Adjusting the color limits enables you to emphasize any particular data range of interest. Adjust the color limits to range from -5 to 2.4832 so that any value lower than the value -5 (the original data ranged from -11.5417 to 2.4832) is mapped into the same color. (See caxis and Axis Color Limits - The CLim Property in Axes Properties in the MATLAB documentation for an explanation of color mapping.)

```
caxis([-5,2.4832])
```

Adding a color bar provides a key for the data-to-color mapping.

```
colorbar('horiz')
```



Connecting Equal Values with Isosurfaces

Isosurfaces are constructed by creating a surface within the volume that has the same value at each vertex. Isosurface plots are similar to contour plots in that they both indicate where values are equal.

Isosurfaces are useful to determine where in a volume a certain threshold value is reached or to observe the spatial distribution of data by selecting various isovalues at which to generate a plot. The isovalue must lie within the range of the volume data.

Create isosurfaces with the isosurface and patch commands.

Example – Isosurfaces in Fluid Flow Data

This example creates isosurfaces in a volume generated by the flow M-file. Generate the volume data with the command

[x,y,z,v] = flow;


To select the isovalue, determine the range of values in the volume data.

min(v(:))
ans =
 -11.5417
max(v(:))
ans =
 2.4832

Through exploration, you can select isovalues that reveal useful information about the data. Once selected, use the isovalue to create the isosurface:

- Use isosurface to generate data that you can pass directly to patch.
- Recalculate the surface normals from the gradient of the volume data to produce better lighting characteristics (isonormals).
- Set the patch FaceColor to red and the EdgeColor to none to produce a smoothly lit surface.
- Adjust the view and add lighting (daspect, view, camlight, lighting).

```
hpatch = patch(isosurface(x,y,z,v,0));
isonormals(x,y,z,v,hpatch)
set(hpatch,'FaceColor','red','EdgeColor','none')
daspect([1,4,4])
view([-65,20])
axis tight
camlight left;
set(gcf,'Renderer','zbuffer'); lighting phong
```




Isocaps Add Context to Visualizations


- "Other Isocap Applications" on page 6-22
- "Defining Isocaps" on page 6-22
- "Example Adding Isocaps to an Isosurface" on page 6-23

Isocaps are planes that are fitted to the limits of an isosurface to provide a visual context for the isosurface. Isocaps show a cross-sectional view of the interior of the isosurface for which the isocap provides an *end cap*.

The following two pictures illustrate the use of isocaps. The first is an isosurface without isocaps.



The second picture shows the effect of adding isocaps to the same isosurface.



Other Isocap Applications

Some additional applications of isocaps are shown in the following examples.

- Isocaps show the interior of a cut-away volume.
- Isocaps cap the end of a volume that would otherwise appear empty.
- Isocaps enhance the visibility of the isosurface limits.

Defining Isocaps

Isocaps, like isosurfaces, are created as patch graphics objects. Use the isocaps command to generate the data to pass to patch. For example,

```
patch(isocaps(voldata,isoval),...
'FaceColor','interp',...
'EdgeColor','none')
```

creates isocaps for the scalar volume data voldata at the value isoval. You should create the isosurface using the same volume data and isovalue to ensure that the edges of the isocaps *fit* the isosurface.

Setting the patch FaceColor property to interp results in a coloring that maps the data values spanned by the isocap to colormap entries. You can also set other patch properties to control the effects of lighting and coloring on the isocaps.

Example – Adding Isocaps to an Isosurface

This example illustrates how to set coloring and lighting characteristics when working with isocaps. There are five basic steps:

- Generate and process your volume data.
- Create the isosurface and isocaps and set patch properties to control the coloring and lighting.
- Create the isocaps and set properties.
- Specify the view.
- Add lights to the scene.

1. Prepare the Data

This example uses a 3-D array of random (rand) data to define the volume data. The data is then smoothed (smooth3).

```
data = rand(12,12,12);
data = smooth3(data,'box',5);
```

2. Create the Isosurface and Set Properties

Use isosurface and patch to create the isosurface and set coloring and lighting properties. Reduce the AmbientStrength, SpecularStrength, and DiffuseStrength of the reflected light to compensate for the brightness of the two light sources used to provide more uniform lighting.

Recalculate the vertex normals of the isosurface to produce smoother lighting (isonormals).

```
isoval = .5;
h = patch(isosurface(data,isoval),...
'FaceColor','blue',...
'EdgeColor','none',...
'AmbientStrength',.2,...
'SpecularStrength',.7,...
'DiffuseStrength',.4);
isonormals(data,h)
```

3. Create the Isocaps and Set Properties

Define the isocaps using the same data and isovalue as the isosurface. Specify interpolated coloring and select a colormap that provides better contrasting colors with the blue isosurface than those in the default colormap (colormap).

```
patch(isocaps(data,isoval),...
'FaceColor','interp',...
'EdgeColor','none')
colormap hsv
```

4. Define the View


Set the data aspect ratio to [1,1,1] so that the display is in correct proportions (daspect). Eliminate white space within the axes and set the view to 3-D (axis tight, view).

```
daspect([1,1,1])
axis tight
view(3)
```

5. Add Lighting

To add fairly uniform lighting, but still take advantage of the ability of light sources to make visible subtle variations in shape, this example uses two lights, one to the left and one to the right of the camera (camlight). Use Phong lighting to produce the smoothest variation of color (lighting). Phong lighting requires the zbuffer renderer.

```
camlight right
camlight left
set(gcf,'Renderer','zbuffer');
lighting phong
```



Visualizing Vector Volume Data

- "Using Scalar Techniques with Vector Data" on page 6-26
- "Specifying Starting Points for Stream Plots" on page 6-27
- "Accessing Subregions of Volume Data" on page 6-30

Vector volume data contains more information than scalar data because each coordinate point in the data set has three values associated with it. These values define a vector that represents both a magnitude and a direction. The velocity of fluid flow is an example of vector data.

MATLAB supports a number of techniques that are useful for visualizing vector data:

- Stream lines trace the path that a massless particle immersed in the vector field would follow.
- Stream particles are markers that trace stream lines and are useful for creating stream line animations.
- Stream ribbons are similar to stream lines, except that the width of the ribbons enables them to indicate twist. Stream ribbons are useful to indicate curl angular velocity.
- Stream tubes are similar to stream lines, but you can also control the width of the tube. Stream tubes are useful for displaying the divergence of a vector field.
- Cone plots represent the magnitude and direction of the data at each point by displaying a conical arrowhead or an arrow.

It is typically the case that these functions best elucidate the data when used in conjunction with other visualization techniques, such as contours, slice planes, and isosurfaces. The examples in this section illustrate some of these techniques.

Using Scalar Techniques with Vector Data

Visualization techniques such as contour slices, slice planes, and isosurfaces require scalar volume data. You can use these techniques with vector data by taking the magnitude of the vectors. For example, the wind data set returns three coordinate arrays and three vector component arrays, u, v, w. In this case, the magnitude of the velocity vectors equals the wind speed at each corresponding coordinate point in the volume.

```
wind_speed = sqrt(u.^2 + v.^2 + w.^2);
```

The array wind_speed contains scalar values for the volume data. The usefulness of the information produced by this approach, however, depends on what physical phenomenon is represented by the magnitude of your vector data.

Specifying Starting Points for Stream Plots


Stream plots (stream lines, ribbons, tubes, and cones or arrows) illustrate the flow of a 3-D vector field. The MATLAB stream plotting routines (streamline, streamribbon, streamtube, coneplot, stream2, stream3) all require you to specify the point at which you want to begin each stream trace.

Determining the Starting Points

Generally, knowledge of your data's characteristics helps you select the starting points. Information such as the primary direction of flow and the range of the data coordinates helps you decide where to evaluate the data.

The streamslice function is useful for exploring your data. For example, these statements draw a slice through the vector field at a z value midway in the range.

```
load wind
zmax = max(z(:)); zmin = min(z(:));
streamslice(x,y,z,u,v,w,[],[],(zmax-zmin)/2)
```



This stream slice plot indicates that the flow is in the positive x direction and also enables you to select starting points in both x and y. You could create similar plots that slice the volume in the x-z plane or the y-z plane to gain further insight into your data's range and orientation.


Specifying Arrays of Starting-Point Coordinates

To specify the starting point for one stream line, you need the x-, y-, and z-coordinates of the point. The meshgrid command provides a convenient way to create arrays of starting points. For example, you could select the following starting points from the wind data displayed in the previous stream slice.

[sx,sy,sz] = meshgrid(80,20:10:50,0:5:15);

This statement defines the starting points as all lying on x = 80, y ranging from 20 to 50, and z ranging from 0 to 15. You can use plot3 to display the locations.

```
plot3(sx(:),sy(:),sz(:),'*r');
axis(volumebounds(x,y,z,u,v,w))
grid; box; daspect([2 2 1])
```




You do not need to use 3-D arrays, such as those returned by meshgrid, but the size of each array must be the same, and meshgrid provides a convenient way to generate arrays when you do not have an equal number of unique values in each coordinate. You can also define starting-point arrays as column vectors. For example, meshgrid returns 3-D arrays.

<pre>[sx,sy,sz] = meshgrid(80,20:10:50,0:5:15);</pre>			
whos			
Name	Size	Bytes	Class
sx	4x1x4	128	double array
sy	4x1x4	128	double array
SZ	4x1x4	128	double array

In addition, you could use 16-by-1 column vectors with the corresponding elements of the three arrays composing the coordinates of each starting point. (This is the equivalent of indexing the values returned by meshgrid as sx(:), sy(:), and sz(:).)

For example, adding the stream lines produces

streamline(x,y,z,u,v,w,sx(:),sy(:),sz(:))



Accessing Subregions of Volume Data

The subvolume function provides a simple way to access subregions of a volume data set. subvolume enables you to select regions of interest based on limits rather than using the colon operator to index into the 3-D arrays that define volumes. Consider the following two approaches to creating the data for a subvolume — indexing with the colon operator and using subvolume.

Indexing with the Colon Operator

When you index the arrays, you work with values that specify the elements in each dimension of the array.

```
load wind
xsub = x(1:10,20:30,1:7);
ysub = y(1:10,20:30,1:7);
zsub = z(1:10,20:30,1:7);
usub = u(1:10,20:30,1:7);
vsub = v(1:10,20:30,1:7);
wsub = w(1:10,20:30,1:7);
```

Using the subvolume Function

subvolume enables you to use coordinate values that you can read from the axes. For example,

```
lims = [100.64 116.67 17.25 28.75 -0.02 6.86];
[xsub,ysub,zsub,usub,vsub,wsub] = subvolume(x,y,z,u,v,w,lims);
```

You can then use the subvolume data as inputs to any function requiring vector volume data.

Stream Line Plots of Vector Data

MATLAB includes a vector data set called wind that represents air currents over North America. This example uses a combination of techniques:

- Stream lines to trace the wind velocity
- Slice planes to show cross-sectional views of the data
- Contours on the slice planes to improve the visibility of slice-plane coloring

Example

1. Determine the Range of the Coordinates

Load the data and determine minimum and maximum values to locate the slice planes and contour plots (load, min, max).

load wind xmin = min(x(:)); xmax = max(x(:)); ymax = max(y(:)); zmin = min(z(:));

2. Add Slice Planes for Visual Context

Calculate the magnitude of the vector field (which represents wind speed) to generate scalar data for the slice command. Create slice planes along the *x*-axis at xmin, 100, and xmax, along the *y*-axis at ymax, and along the *z*-axis at zmin. Specify interpolated face coloring so the slice coloring indicates wind speed, and do not draw edges (sqrt, slice, FaceColor, EdgeColor).

```
wind_speed = sqrt(u.^2 + v.^2 + w.^2);
hsurfaces = slice(x,y,z,wind_speed,[xmin,100,xmax],ymax,zmin);
set(hsurfaces,'FaceColor','interp','EdgeColor','none')
```

3. Add Contour Lines to the Slice Planes

Draw light gray contour lines on the slice planes to help quantify the color mapping (contourslice, EdgeColor, LineWidth).

```
hcont = ...
contourslice(x,y,z,wind_speed,[xmin,100,xmax],ymax,zmin);
set(hcont,'EdgeColor',[.7,.7,.7],'LineWidth',.5)
```

4. Define the Starting Points for the Stream Lines


In this example, all stream lines start at an *x*-axis value of 80 and span the range 20 to 50 in the *y* direction and 0 to 15 in the *z* direction. Save the handles of the stream lines and set the line width and color (meshgrid, streamline, LineWidth, Color).

```
[sx,sy,sz] = meshgrid(80,20:10:50,0:5:15);
hlines = streamline(x,y,z,u,v,w,sx,sy,sz);
set(hlines,'LineWidth',2,'Color','r')
```

5. Define the View

Set up the view, expanding the *z*-axis to make it easier to read the graph (view, daspect, axis).

```
view(3)
daspect([2,2,1])
axis tight
```



See coneplot for an example of the same data plotted with cones.

Displaying Curl with Stream Ribbons

Stream ribbons illustrate direction of flow, similar to stream lines, but can also show rotation about the flow axis by twisting the ribbon-shaped flow line. The streamribbon function enables you to specify a twist angle (in radians) for each vertex in the stream ribbons.

When used in conjunction with the curl function, streamribbon is useful for displaying the curl angular velocity of a vector field. The following example illustrates this technique:

Example

1. Select a Subset of Data to Plot

Load and select a region of interest in the wind data set using subvolume. Plotting the full data set first can help you select a region of interest.

```
load wind
lims = [100.64 116.67 17.25 28.75 -0.02 6.86];
[x,y,z,u,v,w] = subvolume(x,y,z,u,v,w,lims);
```

2. Calculate Curl Angular Velocity and Wind Speed

Calculate the curl angular velocity and the wind speed.

cav = curl(x,y,z,u,v,w); wind speed = sqrt(u.^2 + v.^2 + w.^2);

3. Create the Stream Ribbons

- Use meshgrid to create arrays of starting points for the stream ribbons. See "Starting Points for Stream Plots" in this chapter for information on specifying the arrays of starting points.
- stream3 calculates the stream line vertices with a step size of .5.


- streamribbon scales the width of the ribbon by a factor of 2 to enhance the visibility of the twisting (which indicates curl angular velocity).
- streamribbon returns the handles of the surface objects it creates, which are then used to set the color to red (FaceColor), the color of the surface edges to light gray (EdgeColor), and slightly increase the brightness of the ambient light reflected when lighting is applied (AmbientStrength).

```
[sx sy sz] = meshgrid(110,20:5:30,1:5);
verts = stream3(x,y,z,u,v,w,sx,sy,sz,.5);
h = streamribbon(verts,x,y,z,cav,wind_speed,2);
set(h,'FaceColor','r',...
'EdgeColor',[.7 .7 .7],...
'AmbientStrength',.6)
```

4. Define the View and Add Lighting

- The volumebounds command provides a convenient way to set axis and color limits.
- Add a grid and set the view for 3-D (streamribbon does not change the current view).
- camlight creates a light positioned to the right of the viewpoint and lighting sets the lighting method to Phong (which requires the Z-buffer renderer).

```
axis(volumebounds(x,y,z,wind_speed))
grid on
view(3)
camlight right;
set(gcf,'Renderer','zbuffer'); lighting phong
```



Displaying Divergence with Stream Tubes

Stream tubes are similar to stream lines, except the tubes have width, providing another dimension that you can use to represent information.

By default, MATLAB indicates the divergence of the vector field by the width of the tube. You can also define widths for each tube vertex and thereby map other data to width.

This example uses the following techniques:

- Stream tubes to indicate flow direction and divergence of the vector field in the wind data set
- Slice planes colored to indicate the speed of the wind currents overlaid with contour line to enhance visibility

Inputs include the coordinates of the volume, vector field components, and starting locations for the stream tubes.

Example

1. Load Data and Calculate Required Values

The first step is to load the data and calculate values needed to make the plots. These values include

- The location of the slice planes (maximum x, minimum y, and a value for the altitude)
- The minimum x value for the start of the stream tubes
- The speed of the wind (magnitude of the vector field)

```
load wind
xmin = min(x(:));
xmax = max(x(:));
ymin = min(y(:));
alt = 7.356; % z-value for slice and streamtube plane
wind_speed = sqrt(u.^2 + v.^2 + w.^2);
```

2. Draw the Slice Planes

Draw the slice planes (slice) and set surface properties to create a smoothly colored slice. Use 16 colors from the hsv colormap.

```
hslice = slice(x,y,z,wind_speed,xmax,ymin,alt);
set(hslice,'FaceColor','interp','EdgeColor','none')
colormap hsv(16)
```

3. Add Contour Lines to Slice Planes

Add contour lines (contourslice) to the slice planes. Adjust the contour interval so the lines match the color boundaries in the slice planes:

- Call caxis to get the current color limits.
- Set the interpolation method used by contourslice to linear to match the default used by slice.

```
color_lim = caxis;
cont_intervals = linspace(color_lim(1),color_lim(2),17);
hcont = contourslice(x,y,z,wind_speed,xmax,ymin,...
alt,cont_intervals,'linear');
set(hcont,'EdgeColor',[.4 .4 .4],'LineWidth',1)
```

4. Create the Stream Tubes

Use meshgrid to create arrays for the starting points for the stream tubes, which begin at the minimum x value, range from 20 to 50 in y, and lie in a single plane in z (corresponding to one of the slice planes).

The stream tubes (streamtube) are drawn at the specified locations and scaled to be 1.25 times the default width to emphasize the variation in divergence (width). The second element in the vector [1.25 30] specifies the number of points along the circumference of the tube (the default is 20). You might want to increase this value as the tube size increases, to maintain a smooth-looking tube.

Set the data aspect ratio (daspect) before calling streamtube.


Stream tubes are surface objects, therefore you can control their appearance by setting surface properties. This example sets surface properties to give a brightly lit, red surface.

```
[sx,sy,sz] = meshgrid(xmin,20:3:50,alt);
daspect([1,1,1]) % set DAR before calling streamtube
htubes = streamtube(x,y,z,u,v,w,sx,sy,sz,[1.25 30]);
set(htubes,'EdgeColor','none','FaceColor','r',...
'AmbientStrength',.5)
```

5. Define the View

The final step is to define the view and add lighting (view, axis volumebounds, Projection, camlight).

```
view(-100,30)
axis(volumebounds(x,y,z,wind_speed))
set(gca,'Projection','perspective')
camlight left
```



Creating Stream Particle Animations

A stream particle animation is useful for visualizing the flow direction and speed of a vector field. The "particles" (represented by any of the line markers) trace the flow along a particular stream line. The speed of each particle in the animation is proportional to the magnitude of the vector field at any given point along the stream line:

Example

1. Specify the Starting Points of the Data Range to Plot

This example determines the region of the volume to plot by specifying the appropriate starting points. In this case, the stream plots begin at x = 100, y spans 20 to 50 and in the z = 5 plane. Note that this is not the full volume bounds.

```
load wind
[sx sy sz] = meshgrid(100,20:2:50,5);
```

2. Create Stream Lines to Indicate the Particle Paths

This example uses stream lines (stream3, streamline) to trace the path of the animated particles. This adds a visual context for the animation. Another possibility is to set the EraseMode property of the stream particle to none, which would be useful for a single trace through the volume.

```
verts = stream3(x,y,z,u,v,w,sx,sy,sz);
sl = streamline(verts);
```

3. Define the View

While all the stream lines start in the z = 5 plane, the values of some spiral down to lower values. The following settings provide a clear view of the animation:

• The viewpoint (view) selected shows both the plane containing most stream lines and the spiral.

- Selecting a data aspect ratio (daspect) of [2 2 0.125] provides greater resolution in the z direction to make the stream particles more easily visible in the spiral.
- Set the axes limits to match the data limits (axis) and draw the axis box (box).

```
view(-10.5,18)
daspect([2 2 0.125])
axis tight; box on
```

4. Calculate the Stream Particle Vertices


The first step is to determine the vertices along the stream line where a particle should be drawn. The interpstreamspeed function returns this data based on the stream line vertices and the speed of the vector data. This example scales the velocities by 0.05 to increase the number of interpolated vertices.

Setting the axes DrawMode property to fast enables the animation to run faster.

The streamparticles function sets the following properties:

- Animate to 10 to run the animation 10 times
- ParticleAlignment to on to start all particle traces together
- MarkerEdgeColor to none to draw only the face of the circular marker. Animations usually run faster when marker edges are not drawn.
- MarkerFaceColor to red
- Marker to o, which draws a circular marker. You can use other line markers as well.

```
iverts = interpstreamspeed(x,y,z,u,v,w,verts,0.05);
set(gca,'drawmode','fast');
streamparticles(iverts,15,...
'Animate',10,...
'ParticleAlignment','on',...
'MarkerEdgeColor','none',...
```



Vector Field Displayed with Cone Plots

This example plots the velocity vector cones for the wind data. The graph produced employs a number of visualization techniques:

- An isosurface is used to provide visual context for the cone plots and to provide means to select a specific data value for a set of cones.
- Lighting enables the shape of the isosurface to be clearly visible.
- The use of perspective projection, camera positioning, and view angle adjustments composes the final view.

Example

1. Create an Isosurface

Displaying an isosurface within the rectangular space of the data provides a visual context for the cone plot. Creating the isosurface requires a number of steps:

- Calculate the magnitude of the vector field, which represents the speed of the wind.
- Use isosurface and patch to draw an isosurface illustrating where in the rectangular space the wind speed is equal to a particular value. Regions inside the isosurface have higher wind speeds, regions outside the isosurface have lower wind speeds.
- Use isonormals to compute vertex normals of the isosurface from the volume data rather than calculate the normals from the triangles used to render the isosurface. These normals generally produce more accurate results.
- Set visual properties of the isosurface, making it red and without drawing edges (FaceColor, EdgeColor).

```
load wind
wind_speed = sqrt(u.^2 + v.^2 + w.^2);
hiso = patch(isosurface(x,y,z,wind_speed,40));
isonormals(x,y,z,wind_speed,hiso)
set(hiso,'FaceColor','red','EdgeColor','none');
```

2. Add Isocaps to the Isosurface

Isocaps are similar to slice planes in that they show a cross section of the volume. They are designed to be the end caps of isosurfaces. Using interpolated face color on an isocap causes a mapping of data value to color in the current colormap. To create isocaps for the isosurface, define them at the same isovalue (isocaps, patch, colormap).

```
hcap = patch(isocaps(x,y,z,wind_speed,40),...
'FaceColor','interp',...
'EdgeColor','none');
colormap hsv
```

3. Create First Set of Cones

- Use daspect to set the data aspect ratio of the axes before calling coneplot so MATLAB can determine the proper size of the cones.
- Determine the points at which to place cones by calculating another isosurface that has a smaller isovalue (so the cones are displayed outside the first isosurface) and use reducepatch to reduce the number of faces and vertices (so there are not too many cones on the graph).
- Draw the cones and set the face color to blue and the edge color to none.

```
daspect([1,1,1]);
[f verts] = reducepatch(isosurface(x,y,z,wind_speed,30),0.07);
h1 = coneplot(x,y,z,u,v,w,verts(:,1),verts(:,2),verts(:,3),3);
set(h1,'FaceColor','blue','EdgeColor','none');
```

4. Create Second Set of Cones

- Create a second set of points at values that span the data range (linspace, meshgrid).
- Draw a second set of cones and set the face color to green and the edge color to none.

```
xrange = linspace(min(x(:)),max(x(:)),10);
yrange = linspace(min(y(:)),max(y(:)),10);
zrange = 3:4:15;
[cx,cy,cz] = meshgrid(xrange,yrange,zrange);
h2 = coneplot(x,y,z,u,v,w,cx,cy,cz,2);
set(h2,'FaceColor','green','EdgeColor','none');
```

5. Define the View


- Use the axis command to set the axis limits equal to the minimum and maximum values of the data and enclose the graph in a box to improve the sense of a volume (box).
- Set the projection type to perspective to create a more natural view of the volume. Set the viewpoint and zoom in to make the scene larger (camproj, camzoom, view).

```
axis tight
box on
camproj perspective
camzoom(1.25)
view(65,45)
```

6. Add Lighting

Add a light source and use Phong lighting for the smoothest lighting of the isosurface (Phong lighting requires the Z-buffer renderer). Increase the strength of the background lighting on the isocaps to make them brighter (camlight, lighting, AmbientStrength).

```
camlight(-45,45)
set(gcf,'Renderer','zbuffer');
lighting phong
set(hcap,'AmbientStrength',.6)
```





Index

A

alpha values 4-3 ambient light 3-12 AmbientLightColor property 3-7 illustration 3-12 AmbientStrength property 3-7 illustration 3-12 aspect ratio 2-42 2-58 for realistic objects 2-57 for surface displays 2-55 properties that affect 2-47 specifying 2-52 axes aspect ratio 2-42 2-47 3-D 2-42 properties that affect 2-47 specifying 2-52 camera properties 2-30 controlling the shape of 2-52 default aspect ratio 2-48 limits 2-42 example 2-54 plot box 2-9 position rectangle 2-31 scaling 2-42 stretch-to-fill 2-42 axis 2-42 auto 2-43 equal 2-43 ij 2-43 illustrated examples, 3-D 2-44 image 2-44 manual 2-43 normal 2-44 square 2-43 tight 2-43 vis3d 2-43 xy 2-43 azimuth of viewpoint 2-5 default 2-D 2-6

default 3-D 2-6 limitations 2-8

В

BackFaceLighting property 3-8 illustration 3-14 brighten 1-20

С

camdolly 2-21 camera position, moving 2-31 to 2-32 camera properties 2-30 illustration showing 2-9 camera toolbar 2-10 CameraPosition property 2-30 and perspective 2-32 fly-by 2-32 CameraPositionMode property 2-30 CameraTarget property 2-30 CameraTargetMode property 2-30 CameraUpVector property 2-30 2-34 example 2-35 CameraUpVectorMode property 2-30 CameraViewAngle property 2-30 and perspective 2-33 zooming with 2-33 CameraViewAngleMode property 2-31 2-34 camlookat 2-21 camorbit 2-21 campan 2-21 campos 2-21 camproj 2-21 camroll 2-21 camtarget 2-21 camup 2-21 camva 2-21 camzoom 2-21 CData property

patches 5-14 CDataMapping property 1-18 patches 5-14 colorbar 1-17 colormap 1-15 colormaps altering 1-20 brightening 1-20 brightness component of TV signal 1-21 displaying 1-17 for surfaces 1-15 functions that create 1-16 range of RGB values in 1-15 colors colormaps 1-15 indexed 1-14 to 1-15 direct 1-17 scaled 1-17 interpreted by surfaces 1-15 NTSC encoding of 1-21 of patches 5-14 of surface plots 1-14 scaling algorithm 1-18 specifying for surface plot, example 1-18 truecolor 1-14 specifying 1-21 typical RGB values 1-15 cone plots 6-44 coordinate system and viewpoint 2-5

D

DataAspectRatio property 2-47 example 2-52 DataAspectRatioMode property 2-47 default aspect ratio 2-48 azimuth 2-D 2-6 3-D 2-6 CameraPosition 2-31 CameraTarget 2-31 CameraUpVector 2-31 CameraViewAngle 2-31 elevation 2-D 2-6 3-D 2-6 Projection 2-31 view 2-31 del2 1-19 diffuse reflection 3-11 DiffuseStrength property 3-7 illustration 3-11 direct color mapping 1-18 direction cosines 2-35

E

edge effects and lighting 3-15 EdgeColor property 3-8 EdgeLighting property 3-7 edges of patches 5-17 elevation of viewpoint 2-5 default 2-D 2-6 default 3-D 2-6 limitations 2-8 examples 3-D graph 1-2 axis 2-44 changing CameraPosition 2-32 DataAspectRatio property 2-52 del2 1-19 direction cosines 2-35 displaying real objects 2-55 2-57 linspace 1-10 meshgrid 1-4 1-10 of lighting 3-2 parametric surfaces 1-12 plot3 1-4 PlotBoxAspectRatio property 2-53 specifying truecolor surfaces 1-21 stretch-to-fill 2-52 texture mapping 1-24 unevenly sampled data 1-9 view 2-34

F

FaceColor property 3-8 FaceLighting property 3-7 Faces property 5-8 FaceVertexCData property 5-10 5-14 fly-by effect 2-32

G

Gouraud lighting algorithm 3-9 graphs steps to create 3-D 1-2 griddata 1-10

Η

Hadamard matrix 1-12 hidden 1-13 hidden line removal 1-13

indexed color surfaces 1-14 Infs, avoiding in data 1-7 interpolated colors patches 5-9 indexed vs. truecolor 5-22 isosurface illustrating flow data 6-19

L

Laplacian of a matrix 1-19 light 3-4 lighting 3-2 3-18 algorithms flat 3-9 Gouraud 3-9 Phong 3-9 ambient light 3-12 backface 3-14 diffuse reflection 3-11 important properties 3-4 properties that affect 3-7 reflectance characteristics 3-11 3-14 specular color 3-14 exponent 3-13 reflection 3-11 lighting command 3-10 lines removing hidden 1-13 linspace 1-9

Μ

material command 3-11 mathematical functions visualizing with surface plot 1-7 matrix Hadamard 1-12 representing as surface 1-6 mesh 1-6 meshgrid 1-7 MRI data, visualizing 6-8

Ν

nonuniform data, plotting 1-9 NormalMode property 3-8 NTSC color encoding 1-21

0

orthographic projection 2-37 and Z-buffer 2-39

P

parametric surfaces 1-11 patch behavior of function 5-3 interpreting color 5-4 patches coloring 5-14 edges 5-16 face coloring flat 5-9 interpolated 5-9 indexed color 5-19 direct 5-21 scaled 5-19 interpreting color data 5-19 multifaceted 5-7 single polygons 5-4 specifying faces and vertices 5-8 truecolor 5-22 ways to specify 5-2 perspective projection 2-37 and Z-buffer 2-39 Phong lighting algorithm 3-9 plot box 2-9 plot3 1-4 PlotBoxAspectRatio property 2-47 example 2-53 PlotBoxAspectRatioMode property 2-47 plotting 3-D matrices 1-4 vectors 1-4

nonuniform data 1-9 surfaces 1-6 polygons, creating with patch 5-2 position rectangle 2-9 printing 3-D scenes 2-40 projecting surfaces onto an axis 2-55 Projection property 2-31 projection types 2-37 2-41 camera position 2-38 orthographic 2-37 perspective 2-37 rendering method 2-38

R

realism, adding with lighting 3-2 realistic display of objects 2-57 reflection, specular and diffuse 3-11 Renderer property 1-23 RendererMode property 1-23 RGB color values 1-15 rgbplot 1-20 rotation about viewing axis 2-34 without resizing 2-34

S

scaled color mapping 1-18 slice planes colormapping 6-17 slicing a volume 6-14 specular color 3-14 exponent 3-13 highlight 3-13 reflection 3-11 SpecularColorReflectance property 3-7

illustration 3-14 SpecularExponent property 3-7 illustration 3-13 SpecularStrength property 3-7 illustration 3-11 sphere 1-24starting points for stream plots 6-27 stream line plots 6-32 stream plots starting points 6-27 stretch-to-fill 2-42 overriding 2-51 surf 1-6 surfaces CData 1-24 coloring 1-14 curvature mapped to color 1-19 FaceColor 1-24 parametric 1-11 plotting 1-6 nonuniformly sampled data 1-9 texturemap 1-24

T

texture mapping 1-23 three-dimensional objects, creating with patch 5-2 toolbar, camera 2-10 truecolor patches 5-22 rendering method used for 1-23 surface plots 1-21

V

vectors determined by direction cosines 2-35 vertex normals and back face lighting 3-15 VertexNormals property 3-8 Vertices property 5-8 view 2-5 azimuth of viewpoint 2-5 camera properties 2-30 coordinate system defining 2-5 definition of 2-3 elevation of viewpoint 2-5 example of rotation 2-34 limitation of azimuth and elevation 2-8 limitations using 2-8 MATLAB default behavior 2-31 projection types 2-37 specifying 2-30 specifying with azimuth and elevation 2-5 viewing axis 2-9 moving camera along 2-32 viewpoint, controlling 2-5 to 2-6 2-8 visualizing commands for volume data 6-5 mathematical functions 1-7 steps for volume data 6-4 techniques for volume data 6-4 volume data accessing subregions 6-30 examples of 6-3 **MRI 6-8** scalar 6-7 slicing with plane 6-14 steps to visualize 6-4 techniques for visualizing 6-4 vector 6-26 visualizing 6-3

W

wire frame surface 1-6 1-13

Z

Z-buffer

rendering truecolor 1-23 zooming by setting camera angle 2-33

orthographic projection 2-39 perspective projection 2-39