

Simulink[®] Fixed Point[™] Release Notes

How to Contact The MathWorks



www.mathworks.com Web
comp.soft-sys.matlab Newsgroup
www.mathworks.com/contact_TS.html Technical Support



suggest@mathworks.com Product enhancement suggestions
bugs@mathworks.com Bug reports
doc@mathworks.com Documentation error reports
service@mathworks.com Order status, license renewals, passcodes
info@mathworks.com Sales, pricing, and general information



508-647-7000 (Phone)



508-647-7001 (Fax)



The MathWorks, Inc.
3 Apple Hill Drive
Natick, MA 01760-2098

For contact information about worldwide offices, see the MathWorks Web site.

Simulink® Fixed Point™ Release Notes

© COPYRIGHT 2002–2008 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See www.mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

Patents

The MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

Summary by Version	1
Version 6.0 (R2008b) Simulink® Fixed Point Software	4
Version 5.6 (R2008a) Simulink® Fixed Point Software	10
Version 5.5.1 (R2007b+) Simulink® Fixed Point Software	12
Version 5.5 (R2007b) Simulink® Fixed Point Software	13
Version 5.4.1 (R2007a+) Simulink® Fixed Point Software	16
Version 5.4 (R2007a) Simulink® Fixed Point Software	17
Version 5.3 (R2006b) Simulink® Fixed Point Software	18
Version 5.2.1 (R2006a+) Simulink® Fixed Point Software	19
Version 5.2 (R2006a) Simulink® Fixed Point Software	20
Version 5.0 (R14) Simulink® Fixed Point Software	22
Version 4.1 (R13SP1) Fixed-Point Blockset Software ..	34
Version 4.0.1 (R13+) Fixed-Point Blockset Software ...	37

Version 4.0 (R13) Fixed-Point Blockset Software 40

**Compatibility Summary for Simulink® Fixed Point
Software 45**

Summary by Version

This table provides quick access to what's new in each version. For clarification, see “Using Release Notes” on page 2.

Version (Release)	New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Latest Version V6.0 (R2008b)	Yes Details	Yes Summary	Bug Reports Includes fixes	Printable Release Notes: PDF Current product documentation
V5.6 (R2008a)	Yes Details	No	Bug Reports Includes fixes	No
V5.5.1 (R2007b+)	No	No	Bug Reports Includes fixes	No
V5.5 (R2007b)	Yes Details	Yes Summary	Bug Reports Includes fixes	No
V5.4.1 (R2007a+)	No	No	Bug Reports Includes fixes	No
V5.4 (R2007a)	Yes Details	No	Bug Reports Includes fixes	No
V5.3 (R2006b)	Yes Details	No	Bug Reports	No
V5.2.1 (R2006a+)	No	No	Bug Reports at Web site	No
V5.2 (R2006a)	Yes Details	No	Bug Reports at Web site	No
V5.0 (R14)	Yes Details	Yes Summary	Yes Details	No
V4.1 (R13SP1)	Yes Details	No	Yes Details	No

Version (Release)	New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
V4.0.1 (R13+)	Yes Details	Yes Summary	Fixed bugs	No
V4.0 (R13)	Yes Details	Yes Summary	No bug fixes	No

Using Release Notes

Use release notes when upgrading to a newer version to learn about:

- New features
- Changes
- Potential impact on your existing files and practices

Review the release notes for other MathWorks™ products required for this product (for example, MATLAB® or Simulink®) for enhancements, bugs, and compatibility considerations that also might impact you.

If you are upgrading from a software version other than the most recent one, review the release notes for all interim versions, not just for the version you are installing. For example, when upgrading from V1.0 to V1.2, review the release notes for V1.1 and V1.2.

What's in the Release Notes

New Features and Changes

- New functionality
- Changes to existing functionality

Version Compatibility Considerations

When a new feature or change introduces a reported incompatibility between versions, the **Compatibility Considerations** subsection explains the impact.

Compatibility issues reported after the product is released appear under Bug Reports at the MathWorks Web site. Bug fixes can sometimes result in incompatibilities, so you should also review the fixed bugs in Bug Reports for any compatibility impact.

Fixed Bugs and Known Problems

The MathWorks offers a user-searchable Bug Reports database so you can view Bug Reports. The development team updates this database at release time and as more information becomes available. This includes provisions for any known workarounds or file replacements. Information is available for bugs existing in or fixed in Release 14SP2 or later. Information is not available for all bugs in earlier releases.

Access Bug Reports using your MathWorks Account.

Version 6.0 (R2008b) Simulink Fixed Point Software

This table summarizes what's new in Version 6.0 (R2008b):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	Bug Reports Includes fixes	Printable Release Notes: PDF Current product documentation

New features and changes introduced in this version are

- “Limit of Bits Increased with Embedded MATLAB Function Block” on page 5
- “Limit of Bits Increased with Accelerated Simulation” on page 5
- “Limit of Bits Increased with Code Generation” on page 5
- “Fixed-Point Advisor Enhanced” on page 5
- “Generated Code Enhancement” on page 5
- “Parameter to Lock Output Scaling Added to Six Simulink Blocks” on page 6
- ““What’s This?” Context-Sensitive Help Available for Fixed-Point Tool” on page 6
- “Enhanced Support for Stateflow Charts in the Fixed-Point Tool” on page 7
- “Cell Array No Longer Created When Data Logging Is Enabled in the Fixed-Point Tool” on page 7
- “Name Change for Associated Parameters” on page 8
- “Functions Being Removed in a Future Version” on page 9

Limit of Bits Increased with Embedded MATLAB Function Block

Replacement of Embedded MATLAB™ Function block limit of 32 bits with standard block limit of 128 bits.

Limit of Bits Increased with Accelerated Simulation

Replacement of accelerated simulation limit of 32 bits with normal simulation limit of 128 bits.

Limit of Bits Increased with Code Generation

Replacement of code-generation limit of 32 bits with simulation limit of 128 bits.

Fixed-Point Advisor Enhanced

In R2008b, the Fixed-Point Advisor is enhanced with:

- Improved usability including more descriptive results and intuitive table formatting.
- Improved analysis such as the ability to regenerate simulation data in **Create simulation reference data**.
- Direct links from the Fixed-Point Advisor to the Fixed-Point Tool for improved analysis after the conversion is complete.
- A system selector that allows you to choose the system level from which to start the Fixed-Point Advisor.

For more information, see “Fixed-Point Advisor” in the Simulink® Fixed Point™ documentation.

Generated Code Enhancement

In R2008b, code generation is enhanced to remove excess saturation logic code, reducing RAM and ROM, improving code efficiency.

Parameter to Lock Output Scaling Added to Six Simulink Blocks

For the following Simulink blocks, the dialog box now displays a parameter to lock scaling of outputs against changes by the autoscaling tool:

- Constant
- Data Store Memory
- Inport
- Outport
- Relay
- Signal Specification

For more information about these blocks, see “Block Reference” in the *Simulink Reference*.


“What’s This?” Context-Sensitive Help Available for Fixed-Point Tool

R2008b introduces “What’s This?” context-sensitive help for parameters that appear in the Fixed-Point Tool. This feature provides quick access to a detailed description of the parameters, saving you the time it would take to find the information in the Help browser.

To use the “What’s This?” help:

- 1 Place your cursor over the label of a parameter.
- 2 Right-click. A **What’s This?** context menu appears.

For example, the following figure shows the **What’s This?** context menu appearing after right-clicking the **Percent safety margin (e.g. 10 for 10%)** parameter.



- 3 Click What's This?** A context-sensitive help window appears showing a description of the parameter.

Enhanced Support for Stateflow Charts in the Fixed-Point Tool

You can now control the signal logging of a Simulink subsystem placed inside a Stateflow® chart from the subsystem parent node.

Cell Array No Longer Created When Data Logging Is Enabled in the Fixed-Point Tool

In R2008b, the cell array `FixPtSimRanges` is no longer created automatically in the MATLAB workspace after simulation of a model where data logging is enabled in the Fixed-Point Tool.

Compatibility Considerations

Previously, simulating a model with logging enabled in the Fixed-Point Tool would store maximum values, minimum values, and overflow data in the workspace variable `FixPtSimRanges`. In R2008b, this behavior has changed. However, you can still view this information in one of these ways:

- In the **Contents** pane of the Fixed-Point Tool
- In the MATLAB Command Window by calling the function `showfixptsimranges`

If...	Then...
You do not use scripts to manipulate the data stored in <code>FixPtSimRanges</code>	You have no backward incompatibility
You use scripts to manipulate the data stored in <code>FixPtSimRanges</code>	You must add a function call to <code>showfixptsimranges</code> in your scripts

For example, suppose you have a script as follows:

```
global FixPtSimRanges
outputMaxForBlock1 = FixPtSimRanges{1}.MaxValue;
outputMinForBlock1 = FixPtSimRanges{1}.MinValue;
```

```
pathForBlock1 = FixPtSimRanges{1}.Path;
```

In R2008b, you must add a line to the script:

```
global FixPtSimRanges
showfixptsimranges('quiet');
outputMaxForBlock1 = FixPtSimRanges{1}.MaxValue;
outputMinForBlock1 = FixPtSimRanges{1}.MinValue;
pathForBlock1 = FixPtSimRanges{1}.Path;
```

For more information about `showfixptsimranges`, see “Function Reference” in the *Simulink Fixed Point User’s Guide*.

Name Change for Associated Parameters

The Associated parameters in the Autoscale Information dialog box are now Model-Required parameters. Specifically, the **Shared Associated Parameter Initial Value Max** parameter is now **Shared Model-Required Maximum** and **Associated Parameter Initial Value Max** is **Model-Required Maximum**. The names of the minimum values have changed in the same manner. For more information, see “Reviewing Scaling Proposals” in the Simulink Fixed Point documentation.

Functions Being Removed in a Future Version

These functions will be removed in a future version of Simulink Fixed Point software.

Function Name	What Happens When You Use This Function?	Compatibility Considerations
showfixptsimerrors	Still works in R2008b	Use the Fixed-Point Tool to view overflow data for fixed-point simulations. (See “Fixed-Point Tool” in the <i>Simulink Fixed Point User’s Guide</i> .)
showfixptsimranges	Still works in R2008b	Use the Fixed-Point Tool to view maximum values, minimum values, and overflow data. (See “Fixed-Point Tool” in the <i>Simulink Fixed Point User’s Guide</i> .)

Version 5.6 (R2008a) Simulink Fixed Point Software

This table summarizes what's new in Version 5.6 (R2008a):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	No	Bug Reports Includes fixes	No

New features and changes introduced in this version are

- “Enhanced Fixed-Point Tool” on page 10
- “New Fixed-Point Advisor” on page 11
- “Fixed-Point Enhancements in Simulink Blocks” on page 11

Enhanced Fixed-Point Tool

This release introduces the following enhancements to the Fixed-Point Tool:

- In previous releases, you access the Fixed-Point Tool by selecting **Fixed-Point Settings** from the Simulink **Tools** menu. To display the Fixed-Point Tool in this release, from a model's **Tools** menu, select **Fixed-Point > Fixed-Point Tool**. See “Opening the Fixed-Point Tool” for more information.
- In this release, the Fixed-Point Tool incorporates design minimum and maximum values in its automatic scaling procedure. Typically, you use a model object's **Output minimum** and **Output maximum** parameters to specify this design range. The tool's **Contents** pane displays these values in new columns titled **DesignMin** and **DesignMax**. See “Proposing Scaling” for more information.
- The Fixed-Point Tool provides a new Autoscale Information dialog box. For each model object, this dialog summarizes data type details and explains the tool's scaling proposal. See “Reviewing Scaling Proposals” for more information.

See “Fixed-Point Tool” in the *Simulink Fixed Point User’s Guide* for more information about working with the tool.

New Fixed-Point Advisor

The Fixed-Point Advisor is a new interactive tool you can use to facilitate converting a floating-point model or subsystem to an equivalent fixed-point representation. You can use the Fixed-Point Advisor to prepare a model for conversion and obtain an initial scaling to use as the starting point for refinement and exploration inside the Fixed-Point Tool. For more information, see “Fixed-Point Advisor” in the Simulink Fixed Point documentation.

Fixed-Point Enhancements in Simulink Blocks

This section describes enhancements to fixed-point data type support in Simulink blocks.

Lookup Table (n-D) Block

The Lookup Table (n-D) block now supports fixed-point data types.

Sum Block

The Sum block provides a new parameter for specifying the data type of its accumulator. You can now specify its accumulator data type as any data type that Simulink supports, including fixed-point data types.

Version 5.5.1 (R2007b+) Simulink Fixed Point Software

This table summarizes what's new in Version 5.5.1 (R2007b+):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
No	No	Bug Reports Includes fixes	No

Version 5.5 (R2007b) Simulink Fixed Point Software

This table summarizes what's new in Version 5.5 (R2007b):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	Bug Reports Includes fixes	No

New features and changes introduced in this version are

- “New Signal Logging Options in the Fixed-Point Tool” on page 13
- “Add, Subtract, and Sum Blocks Use an Accumulator Data Type” on page 13
- “Cast Operations with Net Bias Use an Intermediate Data Type” on page 14
- “Non-Matrix-Wise Parameter Scaling Modes Removed” on page 14

New Signal Logging Options in the Fixed-Point Tool

In this release, the Fixed-Point Tool includes new options that provide batch control of signal logging for models and subsystems. These options allow you to enable or disable logging for multiple signals simultaneously, based on the location of signals in a model hierarchy and whether the signals have names. For more information, see the documentation for the `fxptdlg` function in the *Simulink Reference*.

Add, Subtract, and Sum Blocks Use an Accumulator Data Type

In previous releases, the Add, Subtract, and Sum blocks used a user-specified output data type to perform all operations. This behavior might have caused precision loss and saturation during intermediate operations, producing unexpected results. In this release, these blocks use an ideal accumulator data type when performing intermediate operations. Consequently, the

Add, Subtract, and Sum blocks now produce more precise results, and the Real-Time Workshop® product generates less saturation code for them.

Cast Operations with Net Bias Use an Intermediate Data Type

Data type conversions with net bias involve an intermediate addition operation. In previous releases, blocks that perform such casts used the output data type's container to compute the addition operation. This behavior might have caused extra saturation, producing unexpected results. In this release, data type conversions can use an ideal data type when performing all intermediate operations. By reducing or eliminating intermediate saturations, cast operations now produce more accurate results, and the Real-Time Workshop product generates more efficient code for them.

Non-Matrix-Wise Parameter Scaling Modes Removed

In previous releases, the Gain and Weighted Moving Average blocks contained a parameter named **Parameter scaling mode** whose options included the following scaling modes:

- Best Precision: Element-wise
- Best Precision: Row-wise
- Best Precision: Column-wise
- Best Precision: Matrix-wise

In this release, only the **Best Precision: Matrix-wise** setting is available, and it is now simply named **Best precision**. On the **Parameter Attributes** pane of the Gain or Weighted Moving Average block parameter dialog box, use the **Data Type Assistant** to specify **Best precision** for the **Scaling** control.

Compatibility Considerations

Pre-R2007b models that contain Gain or Weighted Moving Average blocks whose **Parameter scaling mode** option specifies a non-matrix-wise setting will be updated automatically when loaded in R2007b. That is, the Simulink software will change non-matrix-wise settings to **Best precision**, which now

represents matrix-wise-best-precision scaling. Consequently, affected blocks might generate results that differ from those obtained in previous releases.

Version 5.4.1 (R2007a+) Simulink Fixed Point Software

This table summarizes what's new in Version 5.4.1 (R2007a+):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
No	No	Bug Reports Includes fixes	No

Version 5.4 (R2007a) Simulink Fixed Point Software

This table summarizes what's new in Version 5.4 (R2007a):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	No	Bug Reports Includes fixes	No

New features and changes introduced in this version are

Fixed-Point Tool

The Fixed-Point Tool is a new interactive graphical environment for analyzing and scaling fixed-point systems, which replaces the Fixed-Point Settings interface in previous releases. To access the tool, from the Simulink model editor **Tools** menu, select **Fixed-Point Settings**. Alternatively, you use the `fxptdlg` function to access the tool. See “Fixed-Point Tool” in *Simulink Fixed Point User's Guide* for a tutorial that demonstrates how to use the new interface.

Version 5.3 (R2006b) Simulink Fixed Point Software

This table summarizes what's new in Version 5.3 (R2006b):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	No	Bug Reports	No

New features and changes introduced in this version are

Fixed-Point Enhancements in Simulink Blocks

This section describes enhancements to fixed-point data type support in Simulink blocks.

Math Function Block

The sqrt operation in the Math Function block supports fixed-point data types.

New Lookup Table Blocks

The new Prelookup and Interpolation Using Prelookup blocks support fixed-point data types.

Version 5.2.1 (R2006a+) Simulink Fixed Point Software

This table summarizes what's new in Version 5.2.1 (R2006a+):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
No	No	Bug Reports at Web site	No

Version 5.2 (R2006a) Simulink Fixed Point Software

This table summarizes what's new in Version 5.2 (R2006a):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	No	Bug Reports at Web site	No

New features and changes introduced in this version are

- “Fixed-Point Block Parameters Supported” on page 20
- “Simplest’ Rounding Mode” on page 20

Fixed-Point Block Parameters Supported

This release allows you to specify fixed-point numbers as the values of Simulink block parameters. In particular, you can specify fixed-point data types in Simulink block parameter dialog boxes and as values of the data type property of `Simulink.Parameter` objects. See “Configuring Blocks with Fixed-Point Parameters” for more information.

‘Simplest’ Rounding Mode

A new `Simplest` rounding mode is available for the **Round integer calculations toward** parameter of some fixed-point Simulink blocks. This rounding mode attempts to reduce or eliminate the need for extra rounding code in your generated code. The `Simplest` rounding mode is currently available for the following blocks:

- Data Type Conversion
- Product
- Lookup Table
- Lookup Table (2-D)
- Lookup Table Dynamic

For more information, refer to “Simplest Rounding” in the product documentation.

Version 5.0 (R14) Simulink Fixed Point Software

This table summarizes what's new in Version 5.0 (R14):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	Yes Details	No

New features and changes introduced in this version are

- “Product Restructuring” on page 22
- “Fixed-Point Blocks Fully Integrated into Simulink Software” on page 23
- “API for User-Written Fixed-Point S-Functions” on page 31
- “Fixed-Point Advisor” on page 31
- “Arithmetic with Non-Zero Bias Fully Supported” on page 31
- “Generated Code for Lookup Tables Uses Less ROM” on page 32
- “Functions Moved to Simulink Software” on page 32
- “Obsolete Functions” on page 33
- “Major Bug Fixes” on page 33

Product Restructuring

The Fixed-Point Blockset has been replaced by two new products, Fixed-Point Toolbox™ and Simulink Fixed Point. This product restructuring reflects the broad expansion of fixed-point capabilities in the MATLAB and Simulink software. The Fixed-Point Toolbox product introduces fixed-point operations to the MATLAB language, and the Simulink Fixed Point product enables fixed-point capabilities across much of the Simulink product family.

The Simulink Fixed Point software requires the Fixed-Point Toolbox software. If you are on maintenance, you will automatically receive both of these new products in place of the Fixed-Point Blockset software.

Fixed-Point Blocks Fully Integrated into Simulink Software

All former Fixed-Point Blockset blocks have been moved into the Simulink block libraries with this release. Each of these blocks, as well as all other Simulink blocks, can be used with or without the Simulink Fixed Point software installed. You can share models with any fixed-point and floating-point Simulink blocks among the users in your organization, whether or not they have the Simulink Fixed Point software installed. However, a Simulink Fixed Point software license is required to take full advantage of the fixed-point features of Simulink blocks. For more information, refer to “Sharing Fixed-Point Models” in the *Simulink Fixed Point User’s Guide*.

The following table lists all of the blocks in the Fixed-Point Blockset software as of Release 13. It tells you the current name of the block in the Simulink software and the Simulink library in which you can find the block. Most blocks have the same name as in the last release; however, some block names have changed.

Former Fixed-Point Blockset Block	Former Fixed-Point Blockset Library	Simulink Block	Simulink Library
Abs	Math	Abs	Math Operations
Accumulator	Calculus	Discrete-Time Integrator	Discrete
Accumulator Resettable	Calculus	Discrete-Time Integrator	Discrete
Accumulator Resettable Limited	Calculus	Discrete-Time Integrator	Discrete
Add	Math	Add	Math Operations
Bit Clear	Bits	Bit Clear	Logic and Bit Operations

Former Fixed-Point Blockset Block	Former Fixed-Point Blockset Library	Simulink Block	Simulink Library
Bit Set	Bits	Bit Set	Logic and Bit Operations
Bitwise Operator	Bits	Bitwise Operator	Logic and Bit Operations
Compare To Constant	Logic & Comparison	Compare To Constant	Logic and Bit Operations
Compare To Zero	Logic & Comparison	Compare To Zero	Logic and Bit Operations
Constant	Sources	Constant	Sources
Conversion	Data Type	Data Type Conversion	Signal Attributes
Conversion Inherited	Data Type	Data Type Conversion Inherited	Signal Attributes
Cosine	Lookup	Cosine	Lookup Tables
Counter Free	Sources	Counter Free-Running	Sources
Counter Limited	Sources	Counter Limited	Sources
Data Type Duplicate	Data Type	Data Type Duplicate	Signal Attributes
Data Type Propagation	Data Type	Data Type Propagation	Signal Attributes
Dead Zone	Nonlinear	Dead Zone	Discontinuities
Dead Zone Dynamic	Nonlinear	Dead Zone Dynamic	Discontinuities
Decrement Real World	Math	Decrement Real World	Additional Math & Discrete / Additional Math: Increment - Decrement
Decrement Stored Integer	Math	Decrement Stored Integer	Additional Math & Discrete / Additional Math: Increment - Decrement

Former Fixed-Point Blockset Block	Former Fixed-Point Blockset Library	Simulink Block	Simulink Library
Decrement Time To Zero	Math	Decrement Time To Zero	Additional Math & Discrete / Additional Math: Increment - Decrement
Decrement To Zero	Math	Decrement To Zero	Additional Math & Discrete / Additional Math: Increment - Decrement
Derivative	Calculus	Discrete Derivative	Discrete
Detect Change	Edge Detect	Detect Change	Logic and Bit Operations
Detect Decrease	Edge Detect	Detect Decrease	Logic and Bit Operations
Detect Fall Negative	Edge Detect	Detect Fall Negative	Logic and Bit Operations
Detect Fall Nonpositive	Edge Detect	Detect Fall Nonpositive	Logic and Bit Operations
Detect Increase	Edge Detect	Detect Increase	Logic and Bit Operations
Detect Rise Nonnegative	Edge Detect	Detect Rise Nonnegative	Logic and Bit Operations
Detect Rise Positive	Edge Detect	Detect Rise Positive	Logic and Bit Operations
Difference	Calculus	Difference	Discrete
Divide	Math	Divide	Math Operations
Dot Product	Math	Dot Product	Math Operations
Filter Direct Form I	Filters	This block is obsolete.	
Filter Direct Form I Time Varying	Filters	This block is obsolete.	

Former Fixed-Point Blockset Block	Former Fixed-Point Blockset Library	Simulink Block	Simulink Library
Filter Direct Form II	Filters	Transfer Fcn Direct Form II	Additional Math & Discrete / Additional Discrete
Filter Direct Form II Time Varying	Filters	Transfer Fcn Direct Form II Time Varying	Additional Math & Discrete / Additional Discrete
Filter First Order	Filters	Transfer Fcn First Order	Discrete
Filter Lead or Lag	Filters	Transfer Fcn Lead or Lag	Discrete
Filter Real Zero	Filters	Transfer Fcn Real Zero	Discrete
FIR	Filters	Weighted Moving Average	Discrete
Gain	Math	Gain	Math Operations
Gateway In	Data Type	Data Type Conversion	Signal Attributes
Gateway In Inherited	Data Type	Data Type Conversion Inherited	Signal Attributes
Gateway Out	Data Type	Data Type Conversion	Signal Attributes
Increment Real World	Math	Increment Real World	Additional Math & Discrete / Additional Math: Increment - Decrement
Increment Stored Integer	Math	Increment Stored Integer	Additional Math & Discrete / Additional Math: Increment - Decrement
Index Vector	Select	Index Vector	Signal Routing
Integer Delay	Delays & Holds	Integer Delay	Discrete

Former Fixed-Point Blockset Block	Former Fixed-Point Blockset Library	Simulink Block	Simulink Library
Integrator Backward	Calculus	Discrete-Time Integrator	Discrete
Integrator Backward Resetable	Calculus	Discrete-Time Integrator	Discrete
Integrator Backward Resetable Limited	Calculus	Discrete-Time Integrator	Discrete
Integrator Forward	Calculus	Discrete-Time Integrator	Discrete
Integrator Forward Resetable	Calculus	Discrete-Time Integrator	Discrete
Integrator Forward Resetable Limited	Calculus	Discrete-Time Integrator	Discrete
Integrator Trapezoidal	Calculus	Discrete-Time Integrator	Discrete
Integrator Trapezoidal Resetable	Calculus	Discrete-Time Integrator	Discrete
Integrator Trapezoidal Resetable Limited	Calculus	Discrete-Time Integrator	Discrete
Interval Test	Logic & Comparison	Interval Test	Logic and Bit Operations
Interval Test Dynamic	Logic & Comparison	Interval Test Dynamic	Logic and Bit Operations
Logical Operator	Logic & Comparison	Logical Operator	Logic and Bit Operations
Lookup Table	Lookup	Lookup Table	Lookup Tables
Lookup Table Dynamic	Lookup	Lookup Table Dynamic	Lookup Tables
Lookup Table (2-D)	Lookup	Lookup Table (2-D)	Lookup Tables

Former Fixed-Point Blockset Block	Former Fixed-Point Blockset Library	Simulink Block	Simulink Library
Matrix Gain	Math	Gain	Math Operations
MinMax	Math	MinMax	Math Operations
MinMax Running Resetable	Math	MinMax Running Resetable	Math Operations
Multiply	Math	Product	Math Operations
Multiply Matrix	Math	Product	Math Operations
Multi-Port Switch	Select	Multiport Switch	Signal Routing
Product	Math	Product	Math Operations
Product of Elements	Math	Product of Elements	Math Operations
Product of Elements Inverted	Math	Product of Elements	Math Operations
Rate Limiter	Nonlinear	Rate Limiter	Discontinuities
Rate Limiter Dynamic	Nonlinear	Rate Limiter Dynamic	Discontinuities
Relational Operator	Logic & Comparison	Relational Operator	Logic and Bit Operations
Relay	Nonlinear	Relay	Discontinuities
Repeating Sequence Interpolated	Sources	Repeating Sequence Interpolated	Sources
Repeating Sequence Stair	Sources	Repeating Sequence Stair	Sources
Sample Rate Probe	Calculus	Weighted Sample Time	Signal Attributes
Sample Time Add	Calculus	Weighted Sample Time	Signal Attributes
Sample Time Divide	Calculus	Weighted Sample Time	Signal Attributes
Sample Time Multiply	Calculus	Weighted Sample Time	Signal Attributes

Former Fixed-Point Blockset Block	Former Fixed-Point Blockset Library	Simulink Block	Simulink Library
Sample Time Probe	Calculus	Weighted Sample Time	Signal Attributes
Sample Time Subtract	Calculus	Weighted Sample Time	Signal Attributes
Saturation	Nonlinear	Saturation	Discontinuities
Saturation Dynamic	Nonlinear	Saturation Dynamic	Discontinuities
Scaling Strip	Data Type	Data Type Scaling Strip	Signal Attributes
Shift Arithmetic	Bits	Shift Arithmetic	Logic and Bit Operations
Sign	Nonlinear	Sign	Math Operations
Sine	Lookup	Sine	Lookup Tables
State-Space	Filters	Fixed-Point State-Space	Additional Math & Discrete / Additional Discrete
Subtract	Math	Subtract	Math Operations
Sum	Math	Sum	Math Operations
Sum of Elements	Math	Sum of Elements	Math Operations
Sum of Elements Negated	Math	Sum of Elements	Math Operations
Switch	Select	Switch	Signal Routing
Tapped Delay	Delays & Holds	Tapped Delay	Discrete
Unary Minus	Math	Unary Minus	Math Operations
Unit Delay	Delays & Holds	Unit Delay	Discrete
Unit Delay Enabled	Delays & Holds	Unit Delay Enabled	Additional Math & Discrete / Additional Discrete

Former Fixed-Point Blockset Block	Former Fixed-Point Blockset Library	Simulink Block	Simulink Library
Unit Delay Enabled External IC	Delays & Holds	Unit Delay Enabled External IC	Additional Math & Discrete / Additional Discrete
Unit Delay Enabled Resettable	Delays & Holds	Unit Delay Enabled Resettable	Additional Math & Discrete / Additional Discrete
Unit Delay Enabled Resettable External IC	Delays & Holds	Unit Delay Enabled Resettable External IC	Additional Math & Discrete / Additional Discrete
Unit Delay External IC	Delays & Holds	Unit Delay External IC	Additional Math & Discrete / Additional Discrete
Unit Delay Resettable	Delays & Holds	Unit Delay Resettable	Additional Math & Discrete / Additional Discrete
Unit Delay Resettable External IC	Delays & Holds	Unit Delay Resettable External IC	Additional Math & Discrete / Additional Discrete
Unit Delay With Preview Enabled	Delays & Holds	Unit Delay With Preview Enabled	Additional Math & Discrete / Additional Discrete
Unit Delay With Preview Enabled Resettable	Delays & Holds	Unit Delay With Preview Enabled Resettable	Additional Math & Discrete / Additional Discrete
Unit Delay With Preview Enabled Resettable External RV	Delays & Holds	Unit Delay With Preview Enabled Resettable External RV	Additional Math & Discrete / Additional Discrete
Unit Delay With Preview Resettable	Delays & Holds	Unit Delay With Preview Resettable	Additional Math & Discrete / Additional Discrete

Former Fixed-Point Blockset Block	Former Fixed-Point Blockset Library	Simulink Block	Simulink Library
Unit Delay Preview Resetable External RV	Delays & Holds	Unit Delay With Preview Resetable External RV	Additional Math & Discrete / Additional Discrete
Wrap To Zero	Nonlinear	Wrap To Zero	Discontinuities
Zero-Order Hold	Delays & Holds	Zero-Order Hold	Discrete

API for User-Written Fixed-Point S-Functions

You can now write your own Simulink C S-functions that directly handle fixed-point data types with a newly published API. For more information, refer to “Writing Fixed-Point S-Functions” in the *Simulink Fixed Point User’s Guide*.

Fixed-Point Advisor

The Simulink Fixed Point software now includes Model Advisor checks to help you to configure your fixed-point models to achieve a more efficient design and optimize your generated code. To use the Model Advisor to check your fixed-point models:

- 1 Select **Model Advisor** from the **Tools** menu of the model you wish to analyze. The Model Advisor appears in the Documents window on the MATLAB desktop.
- 2 Click **Select All** to enable all Model Advisor checks. For fixed-point code generation, the most important check boxes to select are **Identify questionable fixed-point operations**, **Identify blocks that generate expensive saturation and rounding code**, and **Check the Hardware Implementation**.
- 3 Click **Check Model**. Any tips for improving the efficiency of your fixed-point model appear in the browser.

Arithmetic with Non-Zero Bias Fully Supported

Code generation has been enhanced to generate bit-true fixed-point code that supports multiplication, division, and reciprocal for signal and parameters

with non-zero bias. Previously, these cases lead to code generation errors. Code will now be generated for these cases, and that code will make efficient use of just C integer operations.

Generated Code for Lookup Tables Uses Less ROM

In prior releases, the size of the generated code for models that contained lookup tables with similar attributes was larger than necessary. Such lookup tables produced similar algorithms that appeared throughout the code multiple times. In this release, some common algorithms have been placed into functions which are called by the lookup tables. This enables the same code to be reused multiple times. The overall size of the generated code has been reduced through this enhancement.

Functions Moved to Simulink Software

The following former Fixed-Point Blockset functions are now installed with the Simulink software:

- `fixptbestexp`
- `fixptbestprec`
- `fixpt_interp1`
- `fixpt_look1_func_approx`
- `fixpt_look1_func_plot`
- `fixpt_set_all`
- `float`
- `fxptdlg`
- `num2fixpt`
- `sfix`
- `sfrac`
- `sint`
- `ufix`
- `ufrac`

- uint

Obsolete Functions

The functions `fixpt_restore_links` and `fpupdate` are obsolete.

Compatibility Considerations

These functions are no longer needed to update models.

Major Bug Fixes

This section summarizes the major bug fixes introduced in Version 5.0 of the Simulink Fixed Point software.

Simulation Error for 65-Bit+ Multiplication Corrected

In prior releases, fixed-point multiplication could produce the wrong answer under certain simulation conditions. For this error to occur, one input had to have at least 33 bits and the other input at least 32 bits. The correct answer had to be negative, and some additional numerical criteria had to be met. This error could only occur in simulation; it never occurred in generated code. This error has been fully corrected for this release.

Fixed-Point Settings Interface Usable for Large Fonts

In the previous release, the Fixed-Point Settings interface was unusable if your system setup defined large default system fonts. When trying to open the dialog, an error would be reported and the dialog would not appear. The creation of the dialog has now been made robust to large fonts, and this problem is solved.

Lookup Table (2-D) Code Generation Bug Fixed

In a previous release, code generation would error out for the Lookup Table (2-D) block if the input data type had non-zero bias or non-one fractional slope, and the corresponding breakpoints were evenly spaced. This problem has been fixed.

Version 4.1 (R13SP1) Fixed-Point Blockset Software

This table summarizes what's new in Version 4.1 (R13SP1):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	No	Yes Details	No

New features and changes introduced in this version are

- “Improved Treatment of Tunable Parameters” on page 34
- “Generated Code Improved for Lookup Tables and Division” on page 35
- “Major Bug Fixes” on page 35

Improved Treatment of Tunable Parameters

In Release 13, many Simulink and Fixed-Point Blockset blocks were unified. The unified blocks were designed to be fully compatible with models created in earlier releases. However, the unified rules for the treatment of tunable parameters caused compatibility problems for some legacy fixed-point models as discussed in “Backwards Compatibility of Tunable Parameters for Unified Fixed-Point Blocks” on page 37. In this release, these rules have been improved.

A fixed-point model created in Release 12.1 may have experienced problems with tunable parameters when generating code with Versions 5.0 or 5.0.1 of the Real-Time Workshop software. With the current release, a model created in Release 12.1 will be able to generate code without compatibility problems. Please note that the steps described in “Version 4.0.1 (R13+) Fixed-Point Blockset Software” on page 37 of these Release Notes to solve these compatibility problems do not need to be reversed. The new rules are compatible both with legacy fixed-point models from Release 12.1 and with models that used the work-around described for the previous release.

Generated Code Improved for Lookup Tables and Division

The generated code for utilities that support integer and fixed-point math have been improved to reduce the amount of ROM required. In particular, code that supports lookup tables and division has been improved. The generated code for these operations has been restructured to make greater use of shared functions and less use of inlined code.

Major Bug Fixes

This section summarizes the major bug fixes introduced in Version 4.1 of the Fixed-Point Blockset software.

Plot System Dialog Signal Information Corrected

The **Plot System** dialog is a tool that allows fixed-point simulation results to be easily compared against equivalent floating-point simulation results. Access this dialog by opening the **Fixed-Point Settings** interface from the Simulink **Tools** menu, and then clicking the Show plot dialog icon. For the current model, the dialog provides a list of signals that are logged to the workspace by To Workspace blocks, Scope blocks, and root-level Outport blocks. Signals from this list can be selected, and then plotted in three ways.

There are three plot buttons in the **Plot System** dialog. The Plot Signals button shows the simulation results that are collected using the model's specified data types. The Plot Doubles button shows the simulation results that are collected when the model's specified data types are overridden at the root level by True Doubles or Scaled Doubles. The Plot Both button shows both results simultaneously, making it easy to compare fixed-point behavior against idealized floating-point behavior.

In Release 13, the **Plot System** dialog did not always work properly. Clicking any of the three plot buttons could plot the wrong signals or lead to incorrect error messages. These errors have been corrected. Signals are now associated with the correct plot buttons. In addition, the error messages have been changed to give improved instructions on how to collect the data required by each button.

Fixed-Point Settings Interface Now Usable for Large Fonts

In the previous release, the **Fixed-Point Settings** interface was unusable if your system setup defined large default system fonts. When trying to open the dialog, an error would be reported and the dialog would not appear. The creation of the dialog has now been made robust enough to handle large fonts.

Version 4.0.1 (R13+) Fixed-Point Blockset Software

This table summarizes what's new in Version 4.0.1 (R13+):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	Fixed bugs	No

The major change introduced in this version is

Backwards Compatibility of Tunable Parameters for Unified Fixed-Point Blocks

Unified fixed-point blocks with tunable parameters have compatibility problems under certain conditions in Release 13. The problem arises only if a tunable parameter is mapped to a built-in integer or `single` data type. When tunable parameters are mapped to built-in integers or `single`, the code generated by the Real-Time Workshop product will be different for unified blocks than it was for Fixed-Point Blockset blocks in prior releases. There are no compatibility problems if a tunable parameter maps to a nonbuilt-in data type, such as a scaled fixed-point integer.

Compatibility Considerations

Tunable parameters are entered in a Simulink model by specifying the name of a MATLAB variable in a block's dialog. This variable can be either a plain MATLAB variable or a Simulink parameter object. In either case, a numerical value will be defined for this tunable parameter by doing an assignment in MATLAB. MATLAB supports several numerical data types including the eight Simulink built-in numerical data types: `double`, `single`, `int8`, `uint8`, `int16`, `uint16`, `int32`, and `uint32`. One of these eight data types can be used when a value is defined for a MATLAB variable. The effect of the data type of the MATLAB variable is significantly different depending on how the tunable parameter is used in the Simulink model.

For Simulink built-in blocks, the legacy rule is to fully respect the data type used for the value of a MATLAB variable. Whatever data type is used in MATLAB when assigning a value to a variable is also used when declaring that parameter in code generated by the Real-Time Workshop product. The use of that parameter by a block may require the value to be represented using a different data type. If so, additional code is generated to convert the parameter every time it is used by the block. To get the most efficient code for a given block, the value of the MATLAB variable should use the same data type as is needed by the block.

For Fixed-Point Blockset blocks, the legacy rule is to expect no data type information from the MATLAB variable used for the tunable parameter. A fundamental reason for this is that MATLAB does not have native support for fixed-point data types and scaling, so the Simulink built-in legacy rule could not be directly extended to the general fixed-point case. Many fixed-point blocks automatically determine the data type and scaling for parameters based on what leads to the most efficient implementation of a given block. However, certain blocks such as Constant, as well as blocks that use tunable parameters in multiplication, do not imply a unique best choice for the data type and scaling of the parameter. These blocks have provided separate parameters on their dialogs for entering this information.

In Release 13, many Simulink built-in blocks and Fixed-Point Blockset blocks were unified. The Saturation block is an example of a unified block. The Saturation block appears in both the Simulink Library and in the Fixed-Point Blockset Library, but regardless of where it appears it has identical behavior. This identical unified behavior includes the treatment of tunable parameters. The dissimilarity of the legacy rules for tunable parameters has led to a shortcoming in the unified blocks. Unified blocks obey the Simulink legacy rule sometimes and the Fixed-Point Blockset legacy rule at other times. If the block is using the parameter with built-in Simulink data types, then the Simulink legacy rule applies. If the block is using the parameter with nonbuilt-in data types, such as scaled fixed-point data types, then the Fixed-Point Blockset legacy rule applies. This gives full backwards compatibility with one important exception.

The backwards compatibility issue arises when a model created prior to R13 uses a Fixed-Point Blockset block with a tunable parameter, and the data type used by the block happens to be a built-in data type. If the block is unified, it will now handle the parameter using the Simulink legacy rule

rather than the Fixed-Point Blockset legacy rule. This can have a significant impact. For example, suppose the tunable parameter is used in a Saturation block and the data type of the input signal is a built-in `int16`. In prior releases, the Fixed-Point Blockset block would have declared the parameter as an `int16`. For legacy fixed-point models, the MATLAB variables used for tunable parameters invariably gave their value using floating-point `double`. The unified Saturation block would now declare the tunable parameter in the generated code as `double`. This has several negatives. The variable takes up six more bytes of memory as a `double` than as an `int16`. The code for the Saturation block now includes conversions from `double` to `int16` that execute every time the block executes. This increases code size and slows down execution. If the design was intended for use on a fixed-point processor, the use of floating-point variables and floating-point conversion code is likely to be unacceptable. It should be noted that the numerical behavior of the blocks is not changed even though the generated code is different.

For an individual block, the backwards compatibility issue is easily solved. The solution involves understanding that the Simulink legacy rule is being applied. The Simulink legacy rule preserves the data type used when assigning the value to the MATLAB variable. The problem is that an undesired data type will be used in the generated code. To solve this, you should change the way you assign the value of the tunable parameter. Determine what data type is desired in the generated code, then use an explicit type cast when assigning the value in MATLAB. For example, if `int16` is desired in the generated code and the initial value is 3, then assign the value in MATLAB as `int16(3)`. The generated code will now be as desired.

A preliminary step to solving this issue with tunable parameters is identifying which blocks are affected. In most cases, the treatment of the parameter will involve a downcast from `double` to a smaller data type. On the **Diagnostics** tab of the **Simulation Parameters** dialog is a line item called **Parameter downcast**. Setting this item to **Warning** or **None** will help identify the blocks whose tunable parameters require reassignment of their variables.

In R13, the solution described above did not work for three unified blocks: **Switch**, **Look-Up Table**, and **Lookup Table (2-D)**. These blocks caused errors when the value of a tunable parameter was specified using integer data types. This was a false error and has been removed. Using an explicit type cast when assigning a value to the MATLAB variable now solves the issue of generating code with the desired data types.

Version 4.0 (R13) Fixed-Point Blockset Software

This table summarizes what's new in Version 4.0 (R13):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	No bug fixes	No

New features and changes introduced in this version are

- “Installation and Licensing” on page 40
- “Unified Simulink and Fixed-Point Blockset Blocks” on page 41
- “Global Data Type Override and Logging Modes” on page 43
- “Shift Arithmetic Block” on page 44

Installation and Licensing

To support the sharing of models in a large organization, Version 4.0 of the Fixed-Point Blockset product is automatically installed whenever the Simulink software is installed. You can configure models to either take full advantage of all fixed-point features, or to run without a Fixed-Point Blockset software license. Therefore all Simulink software users in your organization can run and work on the same model, regardless of whether they have a Fixed-Point Blockset software license.

You must have a Fixed-Point Blockset software license to run a model if it is configured to log minimums, maximums, or overflows. You control logging with the system-level setting **Logging mode**. If you turn logging off at the top-level system in a model, then no data is logged for any block in any subsystem of the model, and a Fixed-Point Blockset software license is not required. You also need a Fixed-Point Blockset software license to run a model that uses any nonbuilt-in, fixed-point data types. However, you can use the system-level setting **Data type override** to force blocks to use doubles

or `singles` instead of fixed-point data types. Therefore, by turning the **Data type override** parameter on and the **Logging mode** parameter off at the top level of a model, a Simulink software user without a Fixed-Point Blockset software license can run a model with fixed-point enabled blocks. See “Global Data Type Override and Logging Modes” on page 43 for more information on these settings.

If you have a Fixed-Point Blockset software license, you can run bit-true simulations with your models that contain fixed-point enabled blocks. If a Fixed-Point Blockset software license is not available or desired, you can turn logging off and data type override on at the top level of your model and perform idealized floating point-based simulations.

If you have both a Fixed-Point Blockset software license and a Real-Time Workshop software license, you can generate bit-true integer code from your models with fixed-point enabled blocks. If you do not have a Fixed-Point Blockset software license but you do have a Real-Time Workshop software license, you can generate idealized floating-point code from your models with fixed-point enabled blocks.

Unified Simulink and Fixed-Point Blockset Blocks

Many core Simulink and Fixed-Point Blockset blocks with similar functions have been unified in this release. For example, the Sum block in the Simulink Math Operations library and the Sum block in the Fixed-Point Blockset Math library are now the same block. All the functionality from each original block has been maintained in unifying these blocks. Compatibility with fixed-point data types and/or specific fixed-point features are now available with all of these blocks, whether the blocks used are from the Simulink library or the Fixed-Point Blockset library. You do not need to make any changes to your earlier models as a result of this improvement. You can now use any of the unified blocks with either built-in data types or fixed-point data types, which eliminates the need to replace blocks in your models when you want to use different data types. This change does not require Simulink software users to have a Fixed-Point Blockset software license. Refer to “Installation and Licensing” on page 40 for more information.

Fixed-Point Blockset blocks that have been unified no longer have an “F” on their block icon. However, not all Fixed-Point Blockset blocks that have counterparts in the Simulink library have been unified. You can still use the

`fixpt_convert` function to replace nonunified Simulink blocks with their corresponding Fixed-Point Blockset blocks in your models.

Nonunified Fixed-Point Blockset blocks have an advantage over their Simulink library counterparts in that they can handle more data types. As discussed above, you can easily switch them between fixed-point data types and singles or doubles using the global data type override setting. However, you may still want to use the Simulink library counterparts of nonunified Fixed-Point Blockset blocks in some cases, because they support faster simulation times for the data types they handle.

The following table lists the unified blocks in this release, and the Simulink and Fixed-Point Blockset libraries in which they are found.

Block	Simulink Library	Fixed-Point Blockset Library
Abs	Math Operations	Math
Constant	Sources	Sources
Data Store Memory	Signal Routing	N/A
Data Store Read	Signal Routing	N/A
Data Store Write	Signal Routing	N/A
Gain	Math Operations	Math
Inport	Ports & Subsystems, Sources	N/A
Logical Operator	Math Operations	Logic & Comparison
Look-Up Table	Look-Up Tables	LookUp
Look-Up Table (2-D)	Look-Up Tables	LookUp
Manual Switch	Signal Routing	N/A
Memory	Discrete	N/A
Merge	Signal Routing	N/A
Multi-Port Switch	Signal Routing	Select
Outport	Ports & Subsystems, Sinks	N/A
Product	Math Operations	Math

Block	Simulink Library	Fixed-Point Blockset Library
Rate Transition	Signal Attributes	N/A
Relational Operator	Math Operations	Logic & Comparison
Relay	Discontinuities	Nonlinear
Saturation	Discontinuities	Nonlinear
Sign	Math Operations	Nonlinear
Signal Specification	Signal Attributes	N/A
Slider Gain	Math Operations	N/A
Sum	Math Operations	Math
Switch	Signal Routing	Select
Unit Delay	Discrete	Delays & Holds
Zero-Order Hold	Discrete	Delays & Holds

Compatibility Considerations

Breaking library links to Fixed-Point Blockset blocks will almost certainly produce an error when you attempt to run the model. If broken links exist, you will likely uncover them when upgrading to the latest release of the Fixed-Point Blockset software. The `fixpt_restore_links` command can be used to restore links for Fixed-Point Blockset blocks.

Global Data Type Override and Logging Modes

You can now set data type override and logging modes for systems or subsystems in the Fixed-Point Blockset Interface. The **Override data type(s) with doubles** and **Log minimums and maximums** check boxes have been removed from the mask of every Fixed-Point Blockset block.

Compatibility Considerations

The **Override data type(s) with doubles** and **Log minimums and maximums** check boxes have been removed from the mask of every Fixed-Point Blockset block. You can now set these parameters on the system or subsystem level.

When you upgrade to Version 4.0, all doubles override and logging information is cleared from your models. You can reset these controls in the Fixed-Point Blockset Interface for any system or subsystem. Access the Fixed-Point Blockset Interface from the Simulink **Tools** menu, or by typing `fxptdlg('modelName')` at the MATLAB command line.

If you have been getting or setting the block parameters `Db1Over` or `dolog` in your M-code, you must now use the system parameters `DataTypeOverride` and `MinMaxOverflowLogging`.

Shift Arithmetic Block

The Fixed-Point Blockset software now includes the Shift Arithmetic block in the Bits library. The Shift Arithmetic block shifts the bits or binary point of a signal, or both.

Compatibility Summary for Simulink Fixed Point Software

This table summarizes new features and changes that might cause incompatibilities when you upgrade from an earlier version, or when you use files on multiple versions. Details are provided in the description of the new feature or change.

Version (Release)	New Features and Changes with Version Compatibility Impact
Latest Version V6.0 (R2008b)	See the Compatibility Considerations subheading for these new features or changes: <ul style="list-style-type: none"> • “Cell Array No Longer Created When Data Logging Is Enabled in the Fixed-Point Tool” on page 7 • “Functions Being Removed in a Future Version” on page 9
V5.6 (R2008a)	None
V5.5.1 (R2007b+)	None
V5.5 (R2007b)	See the Compatibility Considerations subheading for this new feature or change: <ul style="list-style-type: none"> • “Non-Matrix-Wise Parameter Scaling Modes Removed” on page 14
V5.4.1 (R2007a+)	None
V5.4 (R2007a)	None
V5.3 (R2006b)	None
V5.2.1 (R2006a+)	None
V5.2 (R2006a)	None

Version (Release)	New Features and Changes with Version Compatibility Impact
V5.0 (R14)	See the Compatibility Considerations subheading for this new feature or change: <ul style="list-style-type: none">• “Obsolete Functions” on page 33
V4.1 (R13SP1)	None
V4.0.1 (R13+)	See the Compatibility Considerations subheading for this new feature or change: <ul style="list-style-type: none">• “Backwards Compatibility of Tunable Parameters for Unified Fixed-Point Blocks” on page 37
V4.0 (R13)	See the Compatibility Considerations subheading for each of these new features or changes: <ul style="list-style-type: none">• “Unified Simulink and Fixed-Point Blockset Blocks” on page 41• “Global Data Type Override and Logging Modes” on page 43