

Simulink[®] Verification and Validation[™] Release Notes



MATLAB[®]&SIMULINK[®]

How to Contact MathWorks



Latest news: www.mathworks.com
Sales and services: www.mathworks.com/sales_and_services
User community: www.mathworks.com/matlabcentral
Technical support: www.mathworks.com/support/contact_us



Phone: 508-647-7000



The MathWorks, Inc.
3 Apple Hill Drive
Natick, MA 01760-2098

Simulink[®] Verification and Validation[™] Release Notes

© COPYRIGHT 2004–2015 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See www.mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

Patents

MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

R2015a

Coverage measurement for C S-functions	1-2
Model Advisor checks for MATLAB functions	1-2
IEC 61508, ISO 26262, and EN 50128	1-2
DO-178C/DO-331	1-3
MathWorks Automotive Advisory Board	1-3

R2014b

Model coverage for relational boundary values	2-2
Modeling standard check support for charts that use MATLAB as the action language	2-2
Requirements linking for Simulink data dictionary entries	2-3
Capture and display of requirements details in model highlighting and Web view	2-3

R2014a

Web view option for coverage results	3-2
---	-----

Model Advisor check authoring for model configuration parameters	3-2
Condition coverage for Relational Operator blocks	3-2
Model Advisor checks for MATLAB Code Analyzer messages	3-2
DO-178C/DO-331	3-2
IEC 61508, ISO 26262, and EN 50128	3-2
MathWorks Automotive Advisory Board	3-3
Japanese language localization support	3-3
Enhanced modeling standards checks for display attributes and Math Operations blocks	3-3
MathWorks Automotive Advisory Board check for display attributes	3-3
IEC 61508, ISO 26262, and EN 50128 Check usage of Math Operations blocks	3-3
DO-178C/DO-331 Check usage of Math Operations blocks ...	3-3

R2013b

Requirements traceability for MATLAB code	4-2
Reset option for cumulative model coverage results	4-2
EN 50128 modeling standard checks for railway applications	4-2
Model Advisor checks for MATLAB Function blocks and input/output range specifications	4-2
MATLAB Function blocks	4-2
Import and Output range specifications	4-3
ModelAdvisor.run option for parallel processing	4-3

Model coverage for saturation on integer overflow in Stateflow, MATLAB Function blocks	5-2
rmipref command for managing requirements traceability preferences	5-2
Inclusion of DOORS module-prefix in requirements traceability location identifiers	5-2
Model Advisor navigation between Upgrade Advisor, Performance Advisor, and Code Generation Advisor	5-2
New Model Advisor Checks for Modeling Standards	5-3
IEC 61508 and ISO 26262 Checks	5-3
DO-178C/DO-331 Checks	5-3

Custom labels for requirements links to IBM Rational DOORS	6-2
Requirements linking for Simulink annotations	6-2
Coverage filtering for Stateflow events	6-3
Model Advisor dashboard, providing efficient model guideline checking	6-3
Model Advisor checks for library models and the DO-178C/DO-331 standard	6-3
Library Models	6-3
DO-178C/DO-331 Standard	6-3
HTTP navigation from generated requirements report to requirements and Simulink objects	6-4

Coverage Metric for Blocks with Saturate on Integer Overflow Parameter	7-2
Coverage Support for Simulink Design Verifier Functions Inside Stateflow Charts	7-2
Cumulative Coverage	7-2
Requirements Linking Between Simulink Objects	7-2
URL-Based Navigation From External Requirements Documents to Simulink Objects	7-3
Model Advisor Exclusions	7-3
MathWorks Automotive Advisory Board Checks	7-4

Condition and MCDC Coverage for If Block Conditions	8-2
Capability to Store Requirements Information Outside the Model File	8-2
Selection-Based Linking for Custom Requirements Documents	8-3
Include Requirements Document Data in the Report	8-3
Microsoft Excel Support for Consistency Checking of Simulink References in Requirements Documents	8-3
Requirements Report Default File Names Based on Model Names	8-4

Changed Format for slvnvrntest and slvnvrncgvtest Output	8-4
Conversion of Error and Warning Message Identifiers	8-5
API for Creating Procedural-Based Model Advisor Configurations	8-5
New Model Advisor Checks	8-6
ISO 26262 Checks	8-6
IEC 61508 Checks	8-6
DO-178B Checks	8-6
Check Input Parameters in Model Advisor Report	8-6

R2011a

New Capability to Filter Model Objects from Coverage Collection	9-2
Improved RMI Support for Reference Blocks	9-2
New Function to Merge Logged Component Data	9-2
New and Enhanced Model Advisor Checks	9-2
ISO 26262 Checks	9-3
IEC 61508 Checks	9-3
DO-178B Checks	9-4

R2010bSP1

Bug Fixes

New Functions for Extraction, Signal Logging, Harness Generation, and Test Execution for Model Components .	11-2
New rmi Option to Validate Links in External Requirements Documents	11-3
New Capability to Link a Requirement to Multiple Model Objects	11-3
Viewing Requirements Linked to Model Objects	11-3
Model Coverage Support for Multiple Instances of a Referenced Model	11-3
Model Coverage Support for Stateflow Atomic Subcharts .	11-4
Checking Systems Programmatically With the Model Advisor	11-4
MathWorks Check IDs for the Model Advisor Updated	11-4
New and Enhanced Model Advisor Checks	11-5
MathWorks Automotive Advisory Board Checks	11-5

Coverage Support for Dead Zone Block	12-2
Coverage Support for the Simulink Design Verifier Functions in MATLAB Function Blocks	12-2
Coverage Support for Trigger Ports in Model Blocks	12-2
Requirements Support for MuPAD Documents	12-2

Improved Reports About Requirements Links in Models . .	12-2
New Capability to Tag and Filter Model Requirements . . .	12-2
Improved IBM Rational DOORS Synchronization	12-3
Function rminav Removed	12-3
New and Enhanced Model Advisor Checks	12-3
DO-178B Checks	12-3
IEC 61508 Checks	12-4
MathWorks Automotive Advisory Board Checks	12-4
Modeling Guidelines Documentation Moved into Simulink Documentation	12-4

R2009bSP1

Bug Fixes

R2009b

New Coverage Reporting for Variable-Size Signals	14-2
Model Coverage for Simulink Design Verifier Blocks	14-2
Force Block Reduction Off During Simulation	14-2
Improved RMI Highlighting and Reporting	14-3
Create Custom Configurations Using the Model Advisor Configuration Editor	14-3
Licensing Revised for the Model Advisor	14-3

New and Enhanced Model Advisor Checks	14-4
DO-178B Checks	14-4
IEC 61508 Checks	14-4
Modeling Guidelines for High-Integrity Systems	14-5

R2009a

Recording Coverage for External MATLAB Files	15-2
API for Customizing Model Advisor Results	15-2
New and Enhanced Model Advisor Checks	15-2
DO-178B Checks	15-2
IEC 61508 Checks	15-2
Modeling Standards for MAAB Checks	15-3
MathWorks Automotive Advisory Board Control Algorithm Modeling Guidelines Using MATLAB, Simulink, and Stateflow Included in Help	15-3

R2008b

New and Enhanced Model Advisor Checks	16-2
DO-178B Checks	16-2
IEC 61508 Checks	16-3
MathWorks Automotive Advisory Board Checks	16-3
Improved Selection-Based Linking	16-3
Enhanced Model Coverage Report	16-4

R2008a+

Bug Fixes

R2008a

Enhanced Coverage Support for Referenced Models	18-2
New Requirements Submenu in Model Explorer	18-2
Model Advisor Checks for Modeling Standards Enhanced	18-2
API for Customizing Model Advisor Enhanced	18-3

R2007b+

Bug Fixes

R2007b

Model Coverage Support for Referenced Models	20-2
Model Advisor Checks for Modeling Standards Enhanced	20-2
API for Customizing Model Advisor HTML Reports	20-3

R2007a+

Bug Fixes

R2007a

Bug Fixes

R2006b

Requirement Links Checking	23-2
Modeling Standards Checking	23-2

R2006a

No New Features or Changes

R2015a

Version: 3.9

New Features

Bug Fixes

Coverage measurement for C S-functions

Model coverage is supported for C/C++ S-Functions. The coverage results for S-Function blocks can be viewed in the same report as the rest of the model. For each S-Function block, the report links to a detailed coverage report for the C/C++ code in the block.

To generate coverage report for S-Function blocks:

- 1 When creating S-Functions, enable support for coverage.
- 2 When generating coverage report, enable support for S-Functions.

The following coverage metrics are reported for S-Functions:

- “Cyclomatic Complexity”
- “Condition Coverage (CC)”
- “Decision Coverage (DC)”
- “MCDC Coverage”
- Percentage of statements covered

For more information, see:

- “Model Coverage for C and C++ S-Functions”
- “View Coverage Results for C/C++ Code in S-Function Blocks”

Model Advisor checks for MATLAB functions

The Model Advisor includes checks for MATLAB[®] functions to comply with modeling standards. Previously, the checks verified that only MATLAB Function blocks complied with modeling standards.

IEC 61508, ISO 26262, and EN 50128

The Model Advisor **By Task** folder contains **Modeling Standards for IEC 61508**, **Modeling Standards for ISO 26262**, and **Modeling Standards for EN 50128** checks:

- “Check for MATLAB Function interfaces with inherited properties” replaces **Check for MATLAB Function block interfaces with inherited properties**.
- “Check MATLAB Function metrics” replaces **Check MATLAB Function block metrics**.

DO-178C/DO-331

The Model Advisor **By Task** folder contains **Modeling Standards for DO-178C/DO-331** checks:

- “Check for MATLAB Function interfaces with inherited properties” replaces **Check for MATLAB Function block interfaces with inherited properties**.
- “Check MATLAB Function metrics” replaces **Check MATLAB Function block metrics**.

MathWorks Automotive Advisory Board

The Model Advisor **By Task > Modeling Standards for MAAB > MATLAB Functions** folder contains new checks:

- “Check input and output settings of MATLAB Functions” replaces **Check input and output settings of MATLAB Function blocks**.
- “Check MATLAB Function metrics” replaces **Check MATLAB Function block metrics**.

R2014b

Version: 3.8

New Features

Bug Fixes

Model coverage for relational boundary values

The model coverage tool introduces a relational boundary coverage metric.

Relational boundary coverage examines blocks that have an explicit or implicit relational operation. The coverage also examines Stateflow[®] transitions and MATLAB function blocks that contain a relational operation.

For these blocks, the metric records whether a simulation tests the relational operation with:

- Equal operand values. This part of relational boundary coverage applies only if both operands are integers or fixed-point numbers.
- Operand values that differ by a certain tolerance. This part of relational boundary coverage applies to all operands. For integer and fixed-point operands, the tolerance is fixed. For floating-point operands, you can use either a predefined tolerance or specify your own tolerance value.

For more information, see Relational Boundary Coverage.

Modeling standard check support for charts that use MATLAB as the action language

The following Model Advisor checks now support charts that use MATLAB as the action language.

In the **By Task > Modeling Standards for IEC 61508, Modeling Standards for ISO 26262, and Modeling Standards for EN 50128** folders:

- Check usage of Stateflow constructs

In the **By Task > Modeling Standards for MAAB > Stateflow** folder:

- Check transition actions in Stateflow charts
- Check for unary minus operations on unsigned integers in Stateflow charts
- Check for equality operations between floating-point expressions in Stateflow charts
- Check entry formatting in State blocks in Stateflow charts
- Check return value assignments of graphical functions in Stateflow charts
- Check usage of return values from a graphical function in Stateflow charts

-
- Check for event broadcasts in Stateflow charts
 - Check for comparison operations in Stateflow charts
 - Check usage of exclusive and default states in state machines

Requirements linking for Simulink data dictionary entries

You can create requirements traceability links for entries in Simulink® data dictionaries. In the Model Explorer, right-click a data dictionary entry. From the Requirements Traceability context menu, use selection-based linking shortcuts or the Requirements Link Editor.

Capture and display of requirements details in model highlighting and Web view

Requirements traceability highlighting opens a separate Requirements Details window that shows content from linked documents in Microsoft® Word, Microsoft Excel®, and IBM® Rational® DOORS®. To open the Requirements Details window, in the Simulink Editor, select **Analysis > Requirements Traceability > Highlight Model**. Select a model object with requirements links to see content from linked requirements documents in the Requirements Details window.

If you have Simulink Report Generator™ installed, you can include requirements information in a Web view. In the Simulink Editor, select **File > Export Model to > Web**. In the Web View dialog box, open the **Optional Views** tab and select **Include Requirements view**. Alternatively, in the Simulink Editor, select **Analysis > Requirements Traceability > Generate Web View**.

To view requirements information in a Web view, click a highlighted block (for example, orange highlighted blocks have requirements information). The information for that block appears in the **Informer** pane underneath the model.

R2014a

Version: 3.7

New Features

Bug Fixes

Web view option for coverage results

You can export a Model Coverage Web View for your model. A Web View is an interactive rendition of a model that you can view in a Web browser. A Model Coverage Web View includes model coverage highlighting and analysis information from the Coverage Display Window, as described in View Coverage Results in a Model. For more information, see Export Model Coverage Web View.

Model Advisor check authoring for model configuration parameters

You can create a configuration parameter check by specifying check behavior in an XML data file. To register the check, you use an `sl_customization` file. Previously, only DO-178C/DO-331 checks verified configuration parameter checks. To create the configuration parameter check, see Create Check for Model Configuration Parameters.

Condition coverage for Relational Operator blocks

The model coverage tool records condition coverage for Relational Operator, Compare to Constant, and Compare to Zero blocks. For more information, see Model Objects That Receive Coverage.

Model Advisor checks for MATLAB Code Analyzer messages

DO-178C/DO-331

The Model Advisor **By Task** folder contains these **Modeling Standards for DO-178C/DO-331** checks:

- Check MATLAB Code Analyzer messages
- Check MATLAB code for global variables

IEC 61508, ISO 26262, and EN 50128

The Model Advisor **By Task** folder contains these **Modeling Standards for IEC 61508, Modeling Standards for ISO 26262, and Modeling Standards for EN 50128** checks:

- Check MATLAB Code Analyzer messages
- Check MATLAB code for global variables

MathWorks Automotive Advisory Board

The Model Advisor **By Task > Modeling Standards for MAAB > MATLAB Functions** folder contains this new check:

- Check MATLAB code for global variables

Japanese language localization support

Simulink Verification and Validation™ is available in Japanese for Japanese localized systems. For more information, see Internationalization.

Enhanced modeling standards checks for display attributes and Math Operations blocks

MathWorks Automotive Advisory Board check for display attributes

Check the display attributes of block names checks the display attributes of all blocks to verify compliance with MathWorks® Automotive Advisory Board guideline jc_0061: Display of block names. Previously, the check did not verify compliance of subsystem block names. You can find **Check the display attributes of block names** in the Model Advisor **By Task > Modeling Standards for MAAB > Simulink** folder.

IEC 61508, ISO 26262, and EN 50128 Check usage of Math Operations blocks

IEC 61508, ISO 26262, and EN 50128 Check usage of Math Operations blocks verifies the use of the following Math Operations blocks:

- Abs
- Assignment
- Gain

Previously, the check verified the use of only Abs and Gain blocks. **Check usage of Math Operations blocks** is available in the **By Task > Modeling Standards for IEC 61508, Modeling Standards for ISO 26262, and Modeling Standards for EN 50128** folders.

DO-178C/DO-331 Check usage of Math Operations blocks

DO-178C/DO-331 Check usage of Math Operations blocks verifies the use of the following Math Operation blocks:

- Abs
- Assignment
- Gain
- Math Function
 - Natural logarithm
 - Common (base 10) logarithm
 - Remainder after division
 - Reciprocal

Previously, the check verified the use of only Abs and Gain blocks. The DO-178C/DO-331 **Check usage of Math blocks** verified the use of the Math Function blocks. **Check usage of Math blocks** is no longer available in the **By Task > Modeling Standards for DO-178C/DO-331** folder.

Check usage of Math Operations blocks is available in the Model Advisor **By Task > Modeling Standards for DO-178C/DO-331** folder.

R2013b

Version: 3.6

New Features

Bug Fixes

Compatibility Considerations

Requirements traceability for MATLAB code

When you store requirements traceability data externally, you can create traceability links to and from specific lines of MATLAB code. This capability allows you to include finer granularity in your traceability links. For example, instead of linking between a requirement and a MATLAB Function block, you can link between a requirement and individual lines or sections of code inside a MATLAB Function block.

For more information, see [MATLAB Code Traceability](#).

Reset option for cumulative model coverage results

If you have enabled cumulative model coverage data collection and have existing cumulative coverage data, you can reset that data between simulations. In the Coverage Settings dialog box, on the **Results** tab, click **Clear data**. For more information, see [Specify Model Coverage Options](#).

EN 50128 modeling standard checks for railway applications

The Model Advisor includes model checks for compliance to the EN 50128 standard. The checks are available in the **By Task > Modeling Standards for EN 50128** folder.

Model Advisor checks for MATLAB Function blocks and input/output range specifications

MATLAB Function blocks

The Model Advisor includes checks for MATLAB Function blocks to comply with modeling standards.

IEC 61508, ISO 26262, and EN 50128

The Model Advisor **By Task** folder contains **Modeling Standards for IEC 61508**, **Modeling Standards for ISO 26262**, and **Modeling Standards for EN 50128** checks:

- Check for MATLAB Function block interfaces with inherited properties
- Check MATLAB Function block metrics

DO-178C/DO-331

The Model Advisor **By Task** folder contains **Modeling Standards for DO-178C/DO-331** checks:

-
- Check for MATLAB Function block interfaces with inherited properties
 - Check MATLAB Function block metrics

MathWorks Automotive Advisory Board

The Model Advisor **By Task > Modeling Standards for MAAB > MATLAB Functions** folder contains new checks:

- Check input and output settings of MATLAB Function blocks
- Check MATLAB Function block metrics

Inport and Outport range specifications

The Model Advisor includes checks for MATLAB Function blocks to comply with modeling standards.

IEC 61508, ISO 26262, and EN 50128

The Model Advisor **By Task** folder contains **Modeling Standards for IEC 61508**, **Modeling Standards for ISO 26262**, and **Modeling Standards for EN 50128** checks:

- Check for root Inports with missing range definitions
- Check for root Outports with missing range definitions

ModelAdvisor.run option for parallel processing

If you have a Parallel Computing Toolbox™ license, you can check multiple systems in parallel by using the ModelAdvisor.run function with 'ParallelMode' set to 'On'. By default, 'ParallelMode' is set to 'Off'.

Compatibility Considerations

When you use ModelAdvisor.run with 'ParallelMode' set to 'On', MATLAB automatically creates a parallel pool. Previously, when using ModelAdvisor.run to check multiple systems in parallel, you had to open a parallel pool.

R2013a

Version: 3.5

New Features

Bug Fixes

Model coverage for saturation on integer overflow in Stateflow, MATLAB Function blocks

You can use the model coverage tool to analyze saturation on integer overflow in Stateflow charts and MATLAB Function blocks. During simulation, the software detects the number of times saturation on integer overflow occurs in a Stateflow chart or MATLAB function.

Saturation on integer overflow coverage for Simulink blocks has been supported since R2012a.

To collect saturation on integer overflow coverage for your model, in the Simulink Editor, select **Analysis > Coverage > Settings**. In the Coverage Settings dialog box, in the Coverage metrics group, select **Saturation on integer overflow**.

rmipref command for managing requirements traceability preferences

The `rmipref` function provides a command-line interface that enables you to manage requirements traceability preferences.

For more information on requirements traceability preferences, see The Requirements Settings Dialog Box.

Inclusion of DOORS module-prefix in requirements traceability location identifiers

Unique target identifiers for IBM Rational DOORS requirements links now include DOORS module prefixes, if they are present.

Model Advisor navigation between Upgrade Advisor, Performance Advisor, and Code Generation Advisor

In the Model Advisor window, you can select:

- **Code Generation Advisor** to help configure your model to meet code generation objectives.
- **Upgrade Advisor** to help upgrade models.
- **Performance Advisor** to help improve the simulation performance of your model.

New Model Advisor Checks for Modeling Standards

The Simulink Model Advisor includes new modeling standards checks.

IEC 61508 and ISO 26262 Checks

The Model Advisor **By Task >Modeling Standards for IEC 61508** and **Modeling Standards for ISO 26262** folders contain a new check to replace **Check for questionable constructs**:

- Check for blocks not recommended for C/C++ production code deployment

DO-178C/DO-331 Checks

The Model Advisor **By Task** folder contains a new **Modeling Standards for DO-178C/DO-331** check to replace **Identify questionable blocks within the specified system**:

- Check for blocks not recommended for C/C++ production code deployment

R2012b

Version: 3.4

New Features

Bug Fixes

Compatibility Considerations

Custom labels for requirements links to IBM Rational DOORS

You can specify custom templates for labels of your model requirements links to IBM Rational DOORS. With these templates, in your model, you can include DOORS object property information that you need for your project. The Simulink Verification and Validation software uses requirements links labels in context menus, generated reports, code comments, and consistency checks.

Using the `rmi` command, you can specify a custom template for new DOORS requirements links. You can include user-defined DOORS attributes in the template. For more information, at the MATLAB command prompt, enter:

```
help rmi
```

Under the heading

```
Custom labels for DOORS links
```

the output shows detailed examples for available template settings.

Compatibility Considerations

If you specify a custom template for labels that differs from the default template and your model has existing requirements links to DOORS, requirements consistency checking reports inconsistencies for these links. You can adjust labels for existing DOORS requirements links using the `rmi` command.

Requirements linking for Simulink annotations

You can create requirements links to and from `Simulink.Annotation` objects using the Requirements Management Interface (RMI). Annotations are free-floating text boxes that you can place inside a Simulink model. You can use them to describe requirements for the design. You can then use RMI linking to associate annotations with other Simulink objects or external requirements documents.

Requirements linking for Simulink annotations is enabled only if you configure your model to store requirements data externally. To specify external storage of requirements data for a model, in the Requirements Settings dialog box under **Storage > Default storage location for requirements links data**, select **Store externally (in a separate *.req file)**.

For more information, see [Requirements Linking with Simulink Annotations](#).

Compatibility Considerations

If you have a model that already contains requirements links using the internal storage setting, you cannot use requirements linking for Simulink annotations until you convert that model to use external storage for RMI data. To convert the model, move all existing requirements links in it to an external .req file by selecting **Analysis > Requirements > Move to File**.

Coverage filtering for Stateflow events

You can exclude Stateflow events from recording coverage during Simulink Verification and Validation model coverage collection. For more information, see [Filter a Stateflow Event](#).

Model Advisor dashboard, providing efficient model guideline checking

The Model Advisor dashboard provides a way for you to efficiently check that your model complies with modeling guidelines. You can use the Model Advisor dashboard to run a set of checks on your model without opening the Model Advisor window. For more information, see [Overview of the Model Advisor Dashboard](#).

Model Advisor checks for library models and the DO-178C/DO-331 standard

Library Models

There are Model Advisor checks available to verify the syntax of library models. When you use the Model Advisor to check a library model, the Model Advisor window indicates (~) checks that do not check libraries. To determine if you can run the check on library models, you can also refer to the check documentation, “Capabilities and Limitations”. You cannot use checks that require model compilation. You can use the `ModelAdvisor.Check.SupportLibrary` API to create custom checks for library models.

DO-178C/DO-331 Standard

The Model Advisor also includes model checks for compliance to the DO-178C and DO-331 standards. The new checks are available in the Model Advisor folders:

- **By Task > Modeling Standards for DO-178C/DO-331**

- **By Product > Simulink Verification and Validation > Modeling Standards > Modeling DO-178C/DO-331 Checks**

For information on the DO-178C Software Considerations in Airborne Systems and Equipment Certification and related standards, see Radio Technical Commission for Aeronautics (RTCA) .

Former DO-178B checks are available in the DO-178C/DO-331 Model Advisor folders. The DO-178C/DO-331 checks replace the DO-178B checks.

HTTP navigation from generated requirements report to requirements and Simulink objects

You can set the Requirements Management Interface (RMI) to generate requirements reports that support navigation from system browsers to requirements documents and model objects. You can view and navigate from your generated reports in system browsers as long as the MATLAB internal HTTP server is active on your local host. If you convert your generated report to a PDF file or Microsoft Word document, the navigation links remain valid. For more information, see [Customize Requirements Report Using the RMI Settings and Link from External Applications](#).

R2012a

Version: 3.3

New Features

Bug Fixes

Compatibility Considerations

Coverage Metric for Blocks with Saturate on Integer Overflow Parameter

In R2012a, the Simulink Verification and Validation model coverage tool provides coverage for blocks when you select the **Saturate on Integer Overflow Coverage** parameter option. The software reports the number of times a block saturates on integer overflow during simulation.

To enable this feature, in the Coverage Settings dialog box, on the **Coverage** tab, select the **Saturate on Integer Overflow** option.

Coverage Support for Simulink Design Verifier Functions Inside Stateflow Charts

Simulink Verification and Validation now records coverage for the following Simulink Design Verifier™ functions inside Stateflow charts:

- `sldv.assume`
- `sldv.condition`
- `sldv.prove`
- `sldv.test`

For more information, see [Simulink Design Verifier Coverage](#).

Cumulative Coverage

Simulink Verification and Validation now provides cumulative coverage for identically configured multiple instances of:

- Reusable subsystems
- Stateflow constructs

For more information, see [Creating Cumulative Coverage for Reusable Subsystems and Stateflow Constructs](#).

Requirements Linking Between Simulink Objects

You can now create requirements links between Simulink objects using selection-based linking. This capability allows you to create requirements links between models, enhancing traceability.

To create a requirement link from one model object to another model object:

- 1 Right-click the link destination model object and select **Requirements > Select for linking with Simulink**.
- 2 Right-click the link source model object and select **Requirements > Add link to selected object**.
- 3 Right-click the link source model object again and select **Requirements**. The new link appears at the top of the **Requirements** submenu.

For more information, see *Links Between Models and Requirements*.

URL-Based Navigation From External Requirements Documents to Simulink Objects

In R2012a, the Simulink Verification and Validation tool provides URL-based navigation from external requirements documents to Simulink objects. Previously, the software used ActiveX[®] controls to navigate from Microsoft Office documents to Simulink objects. Now, by default, navigation links from Microsoft Office documents are hyperlinks, allowing for export to HTML or PDF files, and manual copy-paste into other document formats. For more information, see *The Requirement Settings Dialog Box*.

Compatibility Considerations

Compatibility Considerations

Simulink Verification and Validation software continues to recognize navigation links created with ActiveX controls. Additionally, you can create navigation links with ActiveX by selecting **Use ActiveX buttons in Word and Excel (backward compatibility)** in the Requirements Settings dialog box.

Model Advisor Exclusions

You can now exclude model blocks from selected Model Advisor checks, saving time during model development and verification. When a Model Advisor analysis is complete, you can use Model Advisor highlighting to indicate the analysis results for individual Model Advisor checks in the model window. You can exclude blocks from selected checks by right-clicking blocks and selecting exclusions options. For more information, see *Limiting the Scope of a Model Advisor Analysis*.

MathWorks Automotive Advisory Board Checks

In R2012a, the Model Advisor **By Task > Modeling Standards for MAAB > Stateflow** folder no longer includes:

- **Check for annotations with drop shadows.**
- **Check for tunable parameters in Stateflow charts.**
- **Check whether Stateflow events are defined at the chart level or below.** This check is relevant only for software versions previous to release R2009b.

For more information, see MathWorks Automotive Advisory Board Checks in the Simulink Verification and Validation documentation.

R2011b

Version: 3.2

New Features

Bug Fixes

Compatibility Considerations

Condition and MCDC Coverage for If Block Conditions

The If block now receives condition and MCDC coverage on any `if` conditions or `elseif` conditions that contain logical expressions with multiple conditions. Previously, the If block only received decision coverage.

The If block receives coverage as follows:

- The software measures decision coverage for the `if` condition and all `elseif` conditions.
- If the `if` condition or any of the `elseif` conditions contain a logical expression with multiple conditions, such as `u1 & u2 & u3`, the software also measures condition and MCDC coverage for each condition in the expression, for example, `u1`, `u2`, and `u3`.

Capability to Store Requirements Information Outside the Model File

The Requirements Management Interface (RMI) now provides an option to store requirements links information in an external file. The default name for this file is `model_name.req`. External storage allows you to:

- Associate information about links to external requirements documents without modifying the timestamp and version of your model (`.mdl`) file.
- Use different sets of requirements links with the same model by loading links from different files.

To enable external storage of requirements links, in the Requirements Settings dialog box, on the **Storage** tab, select **Store externally (in a separate .req file)**. After setting this option, all models for which you create new requirements links will use external storage.

The RMI provides several new functions that allow you to manage the links in external files:

- `rמידata.map` — Update link information in an external file.
- `rמידata.default` — Set the option for storing requirements link information ('internal' or 'external').
- `rמידata.export` — Move link information for a model to an external file.

Selection-Based Linking for Custom Requirements Documents

If you link to requirements in custom requirements documents, you can now define link type properties that provide selection-based linking capabilities for these documents. Selection-based linking will be available when you:

- Right-click a model object and select Requirements in the context menu.
- Select **Requirements > Edit/Add Links** and create new requirements using the Requirements dialog box.

For more information, see Custom Types of Requirements Documents.

Include Requirements Document Data in the Report

The Requirements Management Interface (RMI) can now include details from requirements text in the requirements report, depending on the type of requirements document:

- Microsoft Word — Include entire paragraph or subsection associated with each linked requirement.
- Microsoft Excel — If the requirement is a single cell in a workbook, include the content from all the preceding cells in that row as a table. If the requirements are in a cell range, include all the content from the cells in that range as a table.
- IBM Rational DOORS — Include the **Object Text** and **Object Heading** attributes for the linked requirements object, and other attributes as specified by the user.

You can specify which DOORS attributes to include or omit from the report using the new `RptgenRMI.doorsAttribs` function.

Before you generate the requirements report, in the Requirements Settings dialog box, on the **Report** tab, select **Include details from linked documents**.

Microsoft Excel Support for Consistency Checking of Simulink References in Requirements Documents

The `rmi` function has a `'checkdoc'` option that checks links from requirements documents to Simulink model objects. This option now checks Microsoft Excel requirements documents, in addition to Microsoft Word documents and IBM Rational DOORS databases.

Requirements Report Default File Names Based on Model Names

When the Requirements Management Interface (RMI) generates an HTML report file, it now uses the model name in the file name. The default name for a requirements report is `model_name_report.html`.

Changed Format for `slvnvruntime` and `slvnvruncgvtest` Output

The output format for `slvnvruntime` and `slvnvruncgvtest` changed in R2011b. In R2011b, the output argument contains the following data for each test case executed in an array of `Simulink.SimulationOutput` objects:

Field	Description
<code>tout_slvnvruncgvtest</code>	Simulation time
<code>xout_slvnvruncgvtest</code>	State data
<code>yout_slvnvruncgvtest</code>	Output signal data
<code>logout_slvnvruncgvtest</code>	Signal logging data for: <ul style="list-style-type: none"> • Signals that are connected to outputs • Signals that are configured for logging on the model

Compatibility Considerations

Compatibility Considerations

If you have scripts that depend on the output from `slvnvruntime` and `slvnvruncgvtest`, you can temporarily specify the output format. Use the nonvisible field `outputFormat` in the `runOpts` structure that `slvnvruntestopts` creates as follows:

```
runOpts = slvnvruntestopts;
runOpts.outputFormat = 'TimeSeries';
slvnvruntest(model_name, sldvData, runOpts);
```

or

```
runOpts = slvnvruntestopts;
runOpts.outputFormat = 'StructureWithTime';
slvnvruntest(model_name, data, runOpts);
```

Conversion of Error and Warning Message Identifiers

For R2011b, error and warning message identifiers have changed in Simulink Verification and Validation.

Compatibility Considerations

Compatibility Considerations

If you have scripts or functions that use message identifiers that changed, you must update the code to use the new identifiers. Typically, message identifiers are used to turn off specific warning messages, or in code that uses a `try/catch` statement and performs an action based on a specific error identifier.

For example, the `SLVNV:simcoverage:InvalidFirstArgument` identifier has changed to `SLVNV:simcoverage:complexityinfo:InvalidFirstArgument`. If your code checks for `SLVNV:simcoverage:InvalidFirstArgument`, you must update it to check for `SLVNV:simcoverage:complexityinfo:InvalidFirstArgument` instead.

To determine the identifier for a warning, run the following command just after you see the warning in the MATLAB command window:

```
[MSG,MSGID] = lastwarn;
```

This command saves the message identifier to the variable `MSGID`.

To determine the identifier for an error that appears at the MATLAB prompt, run the following commands just after you see the error:

```
exception = MException.last;  
MSGID = exception.identifier;
```

Note: Warning messages indicate a potential issue with your code. While you can turn off a warning, a suggested alternative is to change your code so it runs warning-free.

API for Creating Procedural-Based Model Advisor Configurations

In R2011b, there is a new API you can use to create a procedural-based Model Advisor configuration. A procedural-based configuration allows you to specify the order in which

you make changes to your model. You do this by organizing checks into procedures using the procedures API. A check in a procedure does not run until the previous check passes. A procedural-based configuration runs until a check fails, requiring you to modify the model to pass the check and proceed on to the next check. For more information, see [Creating Procedural-Based Model Advisor Configurations](#).

New Model Advisor Checks

The Simulink Model Advisor includes new modeling standards checks.

ISO 26262 Checks

The Model Advisor **By Task** folder contains a new **Modeling Standards for ISO 26262** check:

- Check for inconsistent vector indexing methods

IEC 61508 Checks

The Model Advisor **By Task** folder contains a new **Modeling Standards for IEC 61508** check:

- Check for inconsistent vector indexing methods

DO-178B Checks

The Model Advisor **By Task** folder contains a new **Modeling Standards for DO-178B** check:

- Check for inconsistent vector indexing methods

Check Input Parameters in Model Advisor Report

In R2011b, the Model Advisor report now displays the check input parameters. For more information, see [Viewing and Saving Model Advisor Reports in the Simulink documentation](#).

R2011a

Version: 3.1

New Features

Bug Fixes

New Capability to Filter Model Objects from Coverage Collection

When you simulate your Simulink model, coverage filtering allows you to filter certain model objects from recording coverage. The objects that you specify to exclude are stored in an external file.

- Individual Simulink blocks that receive coverage
- All blocks of a certain type
- Subsystems and all their contents
- Stateflow charts, states, transitions, and temporal events
- Individual library-linked blocks or Stateflow charts
- All reference blocks from a specific block library

Improved RMI Support for Reference Blocks

The Requirements Management Interface (RMI) provides improved support for managing requirements links on reference blocks.

- The new **Library Block Requirements** menu option allows you to view and navigate to requirements associated only with the library block. These links are available to all models that have reference blocks linked to library blocks that themselves have requirements links.
- When you create links from reference blocks to requirements, those links are only associated with the reference block in the current model. You cannot push the requirements links associated with reference blocks back to the library.

New Function to Merge Logged Component Data

The `slvnmmergedata` function allows you to combine logged test cases and counterexamples into a single structure. You can use logged data created by running `slvnmvlogs`, or by running a Simulink Design Verifier analysis.

New and Enhanced Model Advisor Checks

The Simulink Model Advisor includes new and updated modeling standards checks.

ISO 26262 Checks

In the Model Advisor **By Task** folder, there is a new **Modeling Standards for ISO 26262** subfolder.

The subfolder includes the following checks:

- Display model metrics and complexity report
- Check for fully defined interface
- Check for unconnected objects
- Check for questionable constructs
- Check state machine type of Stateflow charts
- Check for model objects that do not link to requirements
- Display configuration management data
- Check usage of Math Operations blocks
- Check usage of Stateflow constructs
- Check usage of Signal Routing blocks
- Check usage of Logic and Bit Operations blocks
- Check usage of Ports and Subsystems blocks

For more information, see the IEC 61508 and ISO 26262 Checks in the Simulink Verification and Validation documentation.

IEC 61508 Checks

Previously, the **IEC 61508 Checks** included the check:

- **Check usage of Simulink constructs**

This check is replaced by the following new checks:

- Check usage of Math Operations blocks
- Check usage of Signal Routing blocks
- Check usage of Logic and Bit Operations blocks
- Check usage of Ports and Subsystems blocks

For more information, see the IEC 61508 and ISO 26262 Checks in the Simulink Verification and Validation documentation.

DO-178B Checks

Previously, the **DO-178B Checks** included the following checks:

- **Check for proper usage of For Iterator blocks**
- **Check for proper usage of While Iterator blocks**
- **Check for proper usage of Relational Operator blocks**
- **Check for proper usage of blocks that compute absolute values**

These previously available checks are replaced by the following new checks:

- Check usage of Math Operations blocks
- Check usage of Signal Routing blocks
- Check usage of Logic and Bit Operations blocks
- Check usage of Ports and Subsystems blocks

Also available are the new checks:

- Check usage of lookup table blocks
- Check Stateflow charts for uniquely defined data objects

For more information, see the DO-178B Checks in the Simulink Verification and Validation documentation.

If, **Switch**, and **Switch Case** blocks are now searched. See the “Check usage of Port and Subsystems” and “Check usage of Signal Routing blocks” checks for more information.

R2010bSP1

Version: 3.0.1

Bug Fixes

R2010b

Version: 3.0

New Features

Bug Fixes

Compatibility Considerations

New Functions for Extraction, Signal Logging, Harness Generation, and Test Execution for Model Components

Several new functions allow you to test the following model components:

- Models referenced from Model blocks
- Atomic subsystems
- Stateflow atomic subcharts

Using these functions, you can create and execute test cases that verify components in order to:

- Debug the component
- Test the robustness of the component
- Achieve 100% model coverage for the component

The new functions perform the following tasks.

Use...	To...
<code>slvnvextract</code>	Extract an atomic subsystem or Stateflow atomic subchart into a new model. This allows you to apply testing and verification techniques that use models or an isolated model component.
<code>slvnvlogsignals</code>	Simulate a Simulink model and log input signals to a model referenced by a Model block. This allows you to capture component inputs when you run a closed-loop system simulation.
<code>slvnvmakeharness</code>	Create a harness model for a component, using logged input signals if specified, or using the default signals. Harness models support graphical editing of input values using Signal Builder blocks.
<code>slvnvmergeharness</code>	Merge test cases and initializations from multiple harness models into a single harness model.
<code>slvnvruntest</code>	Simulate a model, executing the specified test cases to record model coverage and output values.
<code>slvnvruncgvtest</code>	Invoke the Code Generation Verification (CGV) API and execute the specified test cases on the generated code for the model.

New rmi Option to Validate Links in External Requirements Documents

The rmi function has a new option, 'checkdoc', that allows you to validate links from Microsoft Word or IBM Rational DOORS requirements documents to Simulink models.

rmi generates a report of the problems that it detects. The report includes hyperlinks that navigate to the requirements with problems so you can investigate and fix any invalid links.

For more information, see [Checking and Fixing ActiveX-Based Links in Requirements Documents](#).

New Capability to Link a Requirement to Multiple Model Objects

The Requirements Management Interface (RMI) allows you to establish links to selected requirements in Microsoft Word, Microsoft Excel, or IBM Rational DOORS. When you create a link to a selected requirement for multiple model objects, the RMI inserts a single navigation control into the requirements document that links to all the selected model objects. When you activate the navigation control, all linked model objects are highlighted.

Viewing Requirements Linked to Model Objects

If your model, or blocks in your model, has links to requirements in external documents, you can now perform the following tasks without a Simulink Verification and Validation license:

- Highlight objects in a model that have links to requirements
- View information about a requirement
- Navigate from a model object to associated requirements
- Filter requirements highlighting based on keywords

Model Coverage Support for Multiple Instances of a Referenced Model

The Simulink Verification and Validation software records coverage for all instances of a referenced model in Normal simulation mode. The software combines the coverage data from each instance and reports one set of coverage data for the referenced model.

Model Coverage Support for Stateflow Atomic Subcharts

The Simulink Verification and Validation software records coverage for Stateflow atomic subcharts. Atomic subcharts allow you to reuse the same state or subchart across multiple Stateflow charts.

Checking Systems Programmatically With the Model Advisor

Previously, you could check systems programmatically using the `Simulink.ModelAdvisor` class, requiring many steps to check only one system at a time. Now you can check systems using the `ModelAdvisor.run` function. Using this function, you can create a MATLAB file for distribution that specifies a list of checks or a Model Advisor configuration file to run against any number of systems simultaneously.

Additionally, the following functions are available for reviewing results. You can use these functions to determine which checks failed on which systems and archive the results for accessing at a later time.

Use...	To...
<code>ModelAdvisor.run</code>	Run Model Advisor checks on systems.
<code>ModelAdvisor.summaryReport</code>	Open Model Advisor Command-Line Summary report in a web browser.
<code>view</code>	View Model Advisor check results for a system in a web browser.
<code>viewReport</code>	View Model Advisor run results for a system in a web browser, the Model Advisor GUI, or the Command Window.

If you have a Parallel Computing Toolbox license and a multicore machine, to improve performance, you can run the Model Advisor on multiple systems in parallel.

For details, see the `ModelAdvisor.run` reference page and *Checking Systems Programmatically* in the Simulink Verification and Validation documentation.

MathWorks Check IDs for the Model Advisor Updated

The check IDs for MathWorks checks in the Model Advisor are updated to use a consistent format. To easily determine check IDs, use the:

-
- Model Advisor context menu to return the check ID to the workspace.
 - `ModelAdvisor.lookupCheckID` function to look up the new check ID.

For details, see Finding Check IDs in the Simulink Verification and Validation documentation.

Compatibility Considerations

The Model Advisor continues to recognize check IDs that were available prior to R2010b. Using the previous IDs in scripts and functions requires more processing time than if you use the new check IDs. To avoid a performance impact, update scripts and functions to use the new check IDs.

In prior releases, the following `Simulink.ModelAdvisor` methods returned the previous check IDs. In R2010b, the methods return the new check IDs:

```
getCheckAll  
getCheckForGroup  
getCheckForTask  
getSelectedCheck  
verifyCheckRan
```

New and Enhanced Model Advisor Checks

The Simulink Model Advisor includes new and updated verification and validation checks.

MathWorks Automotive Advisory Board Checks

The **MathWorks Automotive Advisory Board** subfolder now includes Check transition actions in Stateflow charts. Use this check to review your system against MAAB guideline `db_0151`: State machine patterns for transition actions.

For more information, see MathWorks Automotive Advisory Board Checks in the Simulink Verification and Validation User's Guide.

R2010a

Version: 2.7

New Features

Bug Fixes

Compatibility Considerations

Coverage Support for Dead Zone Block

The Simulink Verification and Validation software now records coverage for the Dead Zone block.

Coverage Support for the Simulink Design Verifier Functions in MATLAB Function Blocks

The Simulink Verification and Validation software now records coverage for the following Simulink Design Verifier functions in MATLAB Function blocks:

- `sldv.assume`
- `sldv.condition`
- `sldv.prove`
- `sldv.test`

Coverage Support for Trigger Ports in Model Blocks

The Simulink Verification and Validation software records coverage for a triggered Model block.

Requirements Support for MuPAD Documents

The Requirements Management Interface (RMI) now allows you to create requirements links from Simulink model objects to link targets in MuPAD® notebooks.

Improved Reports About Requirements Links in Models

In the requirements reports, the Requirements Management Interface (RMI) reporting capability includes the following improvements:

- Navigation to Simulink model objects with requirements
- Improved table design in requirements reports to accommodate additional detail about requirements

New Capability to Tag and Filter Model Requirements

The Requirements Management Interface (RMI) now allows filtered highlighting and reporting through the user tag attribute. Use this feature to review links with certain

associated user tags. You can configure your settings to automatically apply specified tags when using selection-based linking. Manage these user tags with the new `rmitag` function.

Improved IBM Rational DOORS Synchronization

The Requirements Management Interface (RMI) synchronization of Simulink models with the IBM Rational DOORS software now provides control of change propagation for requirements links created in DOORS or Simulink. You can configure the synchronization to remove outdated links in DOORS whose corresponding links you have already deleted from Simulink. You can also configure the synchronization to remove outdated links in Simulink whose corresponding links you have already deleted from DOORS. When you delete objects with requirements from your Simulink model, you can automatically remove links in DOORS.

Function `rminav` Removed

The Simulink Verification and Validation software no longer supports the `rminav` function. To view model requirements, open the Model Explorer by selecting **View > Model Explorer** or entering the `daexplr` command. In the Model Explorer, click the **Highlight items with requirements on model** icon.

Compatibility Considerations

In R2009b, the `rminav` command opened the Model Explorer.

New and Enhanced Model Advisor Checks

The Simulink Model Advisor includes new and updated verification and validation checks.

DO-178B Checks

The **DO-178B Check** subfolder now includes:

- Check state machine type of Stateflow charts
- Check Stateflow charts for ordering of states and transitions
- Check Stateflow debugging settings

The checks in the **DO-178B Checks** subfolder are reformatted for consistency in the results format.

For more information, see DO-178B Checks in the Simulink Verification and Validation documentation.

IEC 61508 Checks

The **IEC 61508 Checks** subfolder now includes Check state machine type of Stateflow charts.

For more information, see IEC 61508 and ISO 26262 Checks in the Simulink Verification and Validation documentation.

MathWorks Automotive Advisory Board Checks

The **MathWorks Automotive Advisory Board** subfolder now includes:

- Check usage of return values from a graphical function in Stateflow charts
- Check for pointers in Stateflow charts
- Check for event broadcasts in Stateflow charts
- Check for MATLAB expressions in Stateflow charts
- Check for bitwise operations in Stateflow charts
- Check for comparison operations in Stateflow charts
- Check for unary minus operations on unsigned integers in Stateflow charts
- Check for equality operations between floating-point expressions in Stateflow charts

The checks in the **MathWorks Automotive Advisory Board** subfolder are reformatted for consistency in the results format.

For more information, see MathWorks Automotive Advisory Board Checks.

Modeling Guidelines Documentation Moved into Simulink Documentation

The *Modeling Guidelines for High-Integrity Systems* and *MathWorks Automotive Advisory Board Control Algorithm Modeling Guidelines Using MATLAB, Simulink, and Stateflow* documentation is now in the Simulink documentation.

For more information, see Modeling Guidelines in the Simulink documentation.

R2009bSP1

Version: 2.6.1

Bug Fixes

R2009b

Version: 2.6

New Features

Bug Fixes

Compatibility Considerations

New Coverage Reporting for Variable-Size Signals

In R2009b, signal sizes in Simulink models can change during execution to facilitate modeling systems with varying environments, resources, and constraints. The Simulink Verification and Validation software can report the minimum, maximum, and allocated space for all variable-size signals in a model, as recorded during simulation.

To enable this feature, in the Coverage Settings dialog box, on the **Coverage** tab, select the **Signal Size** option.

Model Coverage for Simulink Design Verifier Blocks

The Simulink Verification and Validation model coverage tool can collect model coverage data for Simulink Design Verifier blocks. Using this feature during simulation, you can verify Simulink Design Verifier generated test harnesses and user-defined requirements. The model coverage tool collects model coverage data for the following Simulink Design Verifier blocks:

- Proof Assumption
- Proof Objective
- Test Condition
- Test Objective

To enable this feature, in the Coverage Settings dialog box, on the **Coverage** tab, select **Simulink Design Verifier**.

Force Block Reduction Off During Simulation

The Simulink Verification and Validation software can override the value of the Simulink **Block reduction** parameter. When you set this option, the simulation records coverage for all blocks in the model.

To enable this feature, in the Coverage Settings dialog box, on the **Options** tab, select **Force block reduction off**.

Compatibility Considerations

Previously, model coverage ignored the value of the Simulink **Block reduction** parameter, creating incompatibilities between the model coverage data and the

generated code coverage data. In R2009b, you can select **Force block reduction off** to override the **Block reduction** parameter and collect coverage for all blocks in the model.

Improved RMI Highlighting and Reporting

The Requirements Management Interface (RMI) has the following improvements to its highlighting and reporting capabilities:

- Differential highlighting of blocks and subsystems to easily locate model objects with requirements links
- Real-time update of highlighted view to reflect the current state of the model requirements links
- Improved requirements report that includes a document summary, and details about signal group requirements and objects with missing requirements
- New interface for modifying settings for the requirements report generation that is available to users who do not have a Simulink Report Generator license
- IBM Rational DOORS module paths stored with the requirements information for easier review. For requirement links created before R2009b, the module path information is still saved only in the DOORS module.

Create Custom Configurations Using the Model Advisor Configuration Editor

The Model Advisor Configuration Editor expedites creating and deploying custom configurations of the Model Advisor. The Configuration Editor assists with:

- Adding MathWorks and custom checks to your custom configuration with drag and drop.
- Creating new folders in your custom configuration from a toolbar icon.
- Deploying custom configurations in a MAT file.

For more information, see [Organizing Checks and Folders Using the Model Advisor Configuration Editor](#) and [How to Deploy Custom Configurations in the Simulink Verification and Validation](#) documentation.

Licensing Revised for the Model Advisor

Previously, the Model Advisor populated the list of checks and folders based on the licenses available to you. When you ran checks, the software did not require a license

checkout. In R2009b, the Model Advisor performs a checkout of the Simulink Verification and Validation license when you run Simulink Verification and Validation checks. For a list of Simulink Verification and Validation checks, see Model Advisor Checks in the Simulink Verification and Validation documentation.

Compatibility Considerations

The Model Advisor performs a checkout of a Simulink Verification and Validation license when you run:

- Checks in the Simulink Verification and Validation folder
- Custom checks

If you do not have a Simulink Verification and Validation license available, when you run the check, you see an error message that the required license is not available.

New and Enhanced Model Advisor Checks

The Simulink Model Advisor includes new and updated verification and validation checks.

DO-178B Checks

The **DO-178B Check** subfolder now includes Check safety-related diagnostic settings for model initialization.

The checks in the **DO-178B Checks** subfolder are reformatted for a consistent look and feel to the results.

For more information, see DO-178B Checks in the Simulink Verification and Validation User's Guide.

IEC 61508 Checks

The **IEC 61508 Checks** subfolder now includes Check for model objects that do not link to requirements.

For more information, see IEC 61508 and ISO 26262 Checks in the Simulink Verification and Validation documentation.

Modeling Guidelines for High-Integrity Systems

MathWorks intends this document for engineers developing models and generating code for high-integrity systems using Model-Based Design with MathWorks products. This document describes creating Simulink models that are complete, unambiguous, statistically deterministic, robust, and verifiable. The document focus is on model settings, block usage, and block parameters that impact simulation behavior or code generated by the Real-Time Workshop[®] Embedded Coder[™] product.

These guidelines do not assume that you use a particular safety or certification standard. The guidelines reference some safety standards where applicable, including DO-178B, IEC 61508, and MISRA C.

You can use the Model Advisor to support adhering to these guidelines. Each guideline lists the checks that are applicable to that guideline.

For more information, see “Modeling Guidelines for High-Integrity Systems” in the Simulink Verification and Validation documentation.

R2009a

Version: 2.5

New Features

Bug Fixes

Recording Coverage for External MATLAB Files

MATLAB Function blocks and functions can call external program files. The Model Coverage Tool extends the model coverage capabilities to record coverage for these files. By default, this option is disabled; coverage is not collected for external program files.

Enable this option if you want the software to collect and report coverage for all program files associated with the MATLAB Function blocks. To enable this option, in the Coverage Settings dialog box, select **Coverage for MATLAB files**.

API for Customizing Model Advisor Results

In R2009a, there is a new API to customize the results of the Model Advisor for a common look and feel for all of your customized checks. The API includes templates for you to organize the results in tables or lists. For more information, see Customizing the Model Advisor in the Simulink Verification and Validation User's Guide.

New and Enhanced Model Advisor Checks

The Simulink Model Advisor includes new and updated verification and validation checks.

DO-178B Checks

The **DO-178B Check** subcategory includes the following new checks:

- Check for blocks that do not link to requirements
- Check usage of Math blocks

For more information, see DO-178B Checks in the Simulink Verification and Validation documentation.

IEC 61508 Checks

The checks in the **IEC 61508 Checks** subfolder are reformatted for a consistent look and feel to the results. For more information, see IEC 61508 and ISO 26262 Checks in the Simulink Verification and Validation documentation.

Modeling Standards for MAAB Checks

There is a new **Modeling Standards for MAAB** subfolder in the **By Task** folder of the Model Advisor, which includes subfolders that organize the MAAB checks so you can more easily determine which checks you want to run.

MathWorks Automotive Advisory Board Control Algorithm Modeling Guidelines Using MATLAB, Simulink, and Stateflow Included in Help

The MathWorks Automotive Advisory Board (MAAB) involves major automotive original equipment manufacturers (OEMs) and suppliers in the process of evolving MathWorks controls, simulation, and code generation products, including the Simulink, Stateflow, and Real-Time Workshop products. An important result of the MAAB has been the “MathWorks Automotive Advisory Board Control Algorithm Modeling Guidelines Using MATLAB, Simulink, and Stateflow.” Help for the Simulink Verification and Validation product now includes these guidelines. The MAAB guidelines link to relevant Model Advisor MAAB check help and MAAB check help links to relevant MAAB guidelines.

For more information on the MAAB guidelines, see “MathWorks Automotive Advisory Board Control Algorithm Modeling Guidelines Using MATLAB, Simulink, and Stateflow”. For information on the Model Advisor MAAB checks, see “MathWorks Automotive Advisory Board Checks.”

R2008b

Version: 2.4

New Features

Bug Fixes

New and Enhanced Model Advisor Checks

Context-sensitive help is now available for all Model Advisor checks.

DO-178B Checks

The **DO-178B Check** subcategory includes these new and enhanced checks:

- Check safety-related diagnostic settings for saving — This new check helps enforce and document adherence to coding standards for DO-178B, Software Considerations in Airborne Systems and Equipment Certification.
- Check safety-related diagnostic settings for signal data — This check now checks whether the parameter `SignalRangeChecking` is set to `error`.
- New Action box for the following checks that you can use to automatically fix failures:
 - Check safety-related optimization settings
 - Check safety-related diagnostic settings for solvers
 - Check safety-related code generation settings
 - Check safety-related diagnostic settings for compatibility
 - Check safety-related diagnostic settings for bus connectivity
 - Check safety-related diagnostic settings for signal connectivity
 - Check safety-related diagnostic settings for data store memory
 - Check safety-related diagnostic settings for data used for debugging
 - Check safety-related diagnostic settings for parameters
 - Check safety-related diagnostic settings for signal data
 - Check safety-related diagnostic settings that apply to function-call connectivity
 - Check safety-related diagnostic settings for model referencing
 - Check safety-related model referencing settings
 - Check safety-related diagnostic settings for sample time
 - Check safety-related diagnostic settings for type conversions
 - Check safety-related diagnostic settings for saving

For more information, see DO-178B Checks in the Simulink Verification and Validation documentation.

IEC 61508 Checks

The **IEC 61508 Checks** subcategory includes a new check, Check usage of Stateflow, that helps enforce and document compliance with coding standards for functional safety in electrical, electronic, and programmable electronic systems, as the IEC 61508 standard outlines.

For more information, see IEC 61508 and ISO 26262 Checks in the Simulink Verification and Validation documentation.

MathWorks Automotive Advisory Board Checks

The **MathWorks Automotive Advisory Board Checks** subcategory includes new checks that have been implemented to support the MathWorks Automotive Advisory Board (MAAB) 2.0 rules:

- Check for difference in font and font sizes
- Check Transition orientations in Flowcharts
- Check for display of non-default block attributes
- Check signal line labels
- Check for propagated labels on Signal lines
- Check default Transition placement on Stateflow Charts
- Check setting Stateflow Graphical Function return value
- Check for proper use of Switch Blocks
- Check for proper use of Signal Busses and Mux block usage

For more information, see MathWorks Automotive Advisory Board Checks in the Simulink Verification and Validation documentation.

Improved Selection-Based Linking

To create links between a model and a Microsoft Word or Microsoft Excel file, you can open the file from within both the model and the requirements document. The Requirements Management Interface (RMI) establishes communication with the application when you initiate selection-based linking.

For more information, see Links Between Models and Requirements in the Simulink Verification and Validation documentation.

Enhanced Model Coverage Report

The Model Coverage report now includes information about:

- Model being analyzed
- Simulation optimization options
- Model coverage options

For more information, see [Creating Requirements Reports in the Simulink Verification and Validation documentation](#).

R2008a+

Version: 2.3.1

Bug Fixes

R2008a

Version: 2.3

New Features

Bug Fixes

Enhanced Coverage Support for Referenced Models

The previous release introduced coverage support for referenced models, but only by means of functions that you invoke programmatically. This release includes the following enhancements to coverage support for referenced models:

- Redesigned Coverage Settings dialog box now includes controls that allow you to enable coverage for referenced models graphically.
- New Coverage by Model summary that allows you to navigate easily to coverage reports associated with referenced models in a hierarchy.

New Requirements Submenu in Model Explorer

Full access to the Requirements Management Interface is now available from within the Model Explorer. In this release, a **Requirements** submenu replaces the **Edit requirements** item that appears in Model Explorer context menus. This new submenu provides several options for adding requirements to model elements and specifying link preferences. This same submenu is available by right-clicking objects in a Simulink model or a Stateflow chart.

Model Advisor Checks for Modeling Standards Enhanced

The Simulink Model Advisor has been enhanced with new and updated verification and validation checks.

- In the Task Hierarchy tree, the check category **By Product > Simulink Verification and Validation > Modeling Standards** includes the new subcategory **IEC 61508 Checks**.
- The **IEC 61508 Checks** subcategory includes new checks that help enforce and document adherence to coding standards for functional safety in electrical, electronic, and programmable electronic systems, as the IEC 61508 standard outlines. For descriptions of the IEC 61508 checks, see Model Advisor Checks in the Simulink Verification and Validation documentation.
- The IEC 61508 checks also appear under the new category **By Task > Model-Based Design for IEC 61508**.
- Some **MathWorks Automotive Advisory Board Checks** have been updated.

For Information on How To...	See...
Develop models and code that comply with industry standards and guidelines, such as the IEC 61508 standard and MathWorks Automotive Advisory Board (MAAB) guidelines	Guidelines and Standards in the Real-Time Workshop Embedded Coder documentation
Use the Model Advisor	Consulting the Model Advisor in Simulink User's Guide
Customize the Model Advisor with your own tasks and checks	Customizing the Model Advisor in the Simulink Verification and Validation User's Guide

API for Customizing Model Advisor Enhanced

R2008a provides an enhanced API that allows you to customize the behavior of the Model Advisor for checking and reporting on how well your Simulink models are optimized for simulation and code generation. The API provides classes and functions for defining custom checks and tasks, and writing your own callback functions. For more information, see Customizing the Model Advisor in the Simulink Verification and Validation User's Guide.

R2007b+

Version: 2.2.1

Bug Fixes

R2007b

Version: 2.2

New Features

Bug Fixes

Model Coverage Support for Referenced Models

This release introduces model coverage support for referenced models that operate in Normal mode. That is, you can now record coverage for Model blocks whose **Simulation mode** parameter specifies `Normal`. Toward that end, this release provides three new functions:

- `cvsimref`
- `cv.cvdatagroup`
- `cv.cvtestgroup`

For more information, see *Using Model Coverage Commands for Referenced Models in the Simulink Verification and Validation User's Guide*.

Model Advisor Checks for Modeling Standards Enhanced

The Simulink Model Advisor has been enhanced with new and updated verification and validation checks.

- In the Task Hierarchy tree, the check category **By Product > Simulink Verification and Validation > Modeling Standards** includes two new subcategories: **DO-178B Checks** and **MathWorks Automotive Advisory Board Checks**.
- The **DO-178B Checks** subcategory includes new checks that help enforce and document adherence to coding standards for DO-178B, Software Considerations in Airborne Systems and Equipment Certification. If a piece of software will be flying on a commercial aircraft, the development and verification process must comply with DO-178B. For descriptions of the DO-178B checks, see *Model Advisor Checks in the Simulink Verification and Validation documentation*.
- The DO-178B checks also appear under the new category **By Task > Safety Critical for DO-178B**.
- Checks listed under **By Product > Simulink Verification and Validation > Modeling Standards** in earlier releases, appear under the new subcategory **MathWorks Automotive Advisory Board Checks**. These checks verify that Simulink block diagrams adhere to style guidelines published by the MathWorks Automotive Advisory Board (MAAB).
- Some **MathWorks Automotive Advisory Board Checks** have been updated. For example, the check for “hd_0001, Prohibited Simulink Sink and Data Store blocks”

was modified to allow Data Store Memory, Data Store Read, and Data Store Write blocks and the check for “db_0146, Triggered or enabled subsystems” was modified to include For Iterator, While Iterator, and Case blocks.

For Information on How To...	See...
Use the Model Advisor	Consulting the Model Advisor in Simulink User's Guide
Customize the Model Advisor with your own tasks and checks	Customizing the Model Advisor in the Simulink Verification and Validation User's Guide

API for Customizing Model Advisor HTML Reports

This release provides a new API that allows you to customize Model Advisor HTML reports. The API provides classes and methods for formatting custom HTML reports, making it easier to create, understand, and maintain Model Advisor HTML reports. See [Formatting Model Advisor Results](#) in the Simulink Verification and Validation User's Guide.

R2007a+

Version: 2.1.1

Bug Fixes

R2007a

Version: 2.1

Bug Fixes

R2006b

Version: 2.0

New Features

Bug Fixes

Requirement Links Checking

This release introduces Model Advisor tasks for ensuring the consistency and validity of requirement links in a Simulink block diagram. These checks enable you to identify and fix the following situations:

- The requirements document is missing.
- The location (e.g., bookmark, line number, anchor) specified within the requirements document is invalid.
- The description of a selection-based link does not match its requirements document text.
- The requirements document path does not match your preferred path type (i.e., absolute or relative).

See Consulting the Model Advisor in Simulink User's Guide for more information about using Model Advisor.

Modeling Standards Checking

This release introduces Model Advisor tasks for ensuring that a Simulink block diagram adheres to the style guidelines published by the MathWorks Automotive Advisory Board (MAAB). See Consulting the Model Advisor in Simulink User's Guide for more information about using Model Advisor. For information about the MAAB modeling style guidelines, see <http://www.mathworks.com/industries/auto/maab.html>.

R2006a

Version: 1.1.2

No New Features or Changes

