
MATLAB® Compiler SDK™

Java User's Guide



MATLAB®



How to Contact MathWorks



Latest news: www.mathworks.com

Sales and services: www.mathworks.com/sales and services

User community: www.mathworks.com/matlabcentral

Technical support: www.mathworks.com/support/contact_us

T

Phone: 508-647-7000



The MathWorks, Inc. 1 Apple Hill Drive Natick, MA 01760-2098

MATLAB® Compiler SDK™ Java User's Guide

© COPYRIGHT 2006-2019 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See www.mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

Patents

MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

Revision History

March 2015	Online only	New for Version 6.0 (Release 2015a)
September 2015	Online only	Revised for Version 6.1 (Release 2015b)
October 2015	Online only	Rereleased for Version 6.0.1 (Release
		2015aSP1)
March 2016	Online only	Revised for Version 6.2 (Release 2016a)
September 2016	Online only	Revised for Version 6.3 (Release R2016b)
March 2017	Online only	Revised for Version 6.3.1 (Release R2017a)
September 2017	Online only	Revised for Version 6.4 (Release R2017b)
March 2018	Online only	Revised for Version 6.5 (Release R2018a)
September 2018	Online only	Revised for Version 6.6 (Release R2018b)
March 2019	Online only	Revised for Version 6.6.1 (Release R2019a)
September 2019	Online only	Revised for Version 6.7 (Release R2019b)

Contents

Over	view
Product Overview	1-2 1-2 1-2
Configure Your Java Environment Install the Required JDK Set JAVA_HOME Set the CLASSPATH Configure the Native Library Path Variables	1-3 1-3 1-4 1-4 1-5
Programn	ning
MATLAB Compiler SDK and the JVM	2-2
Integrate a Java Package into an Application	2- 3
About the MATLAB Compiler SDK Java API	2-8
You Create Them?	2-8
Conversion Classes	2-8 2-10
Compiler SDK Product	2-10
	2-11

Pass Arguments To and From Java	2-1 3
Format	2-1 3
Manual Conversion of Data Types	2-1 3
Automatic Conversion to a MATLAB Type	2-14
Specify Optional Arguments	2-16
Handle Return Values	2-20
Pass Java Objects by Reference	2-25
MATLAB Array	2-25
Wrap and Pass Objects to MATLAB	2-2 5
Use Multiple Packages in Single Application	2-30
Work with MATLAB Function Handles	2-30
Work with Objects	2-32
Error Handling	2-35
Error Overview	2-35
Handling Checked Exceptions	2-35
Handling Unchecked Exceptions	2-38
Alternatives to Using of System.exit	2-40
Manage MATLAB Resources	2-41
Why MATLAB Resources Need to be Managed	2-41
Creating MATLAB Objects	2-41
Disposing of MATLAB Objects	2-42
MATLAB Runtime User Data Interface	2-44
Supply Run-Time Profile Information for Parallel Computing	
Toolbox Applications	2-45
Step 1: Write Your Parallel Computing Toolbox Code	2-45
Step 1: Write Tour Parallel Computing Toolbox Code	2-46
Step 2: Set the Faraner Computing Toolbox Frome	
the Command Line Compiler	2-46
Step 4: Write the Java Driver Application	2-47
Dynamically Specify Options to the MATLAB Runtime	2-50
What Options Can You Specify?	2-50
Setting and Retrieving MATLAB Runtime Option Values Using	
MWApplication	2-50
Data Conversion Between Java and MATLAB	2-53
Ωνατιίου	2-53

Call MWArray Methods	2-53 2-54
Cat Iava Dranautias	2-55
Set Java Properties	
How to Set Java System Properties	2-55
Ensure a Consistent GUI Appearance	2-55
Execution of Applications that Create Figures	2-57
Ensuring Multi-Platform Portability	2-59
Deployable Archive Embedding and Extraction	2-61
Overview	2-61
Use MWComponentOptions Class to Indicate Extraction Options	
II-a Farinamant Variable to Indicate Fator stick Ontions	2-61
Use Environment Variables to Indicate Extraction Options	2-63
For More Information	2-64
	2-65
Explore the Javadoc Distribute Integrated Java Applicat	
Distribute Integrated Java Applicat Package Java Applications	ions
Distribute Integrated Java Applicat Package Java Applications	ions 3-2
Distribute Integrated Java Applicat Package Java Applications	3-2 3-3
Distribute Integrated Java Applicat Package Java Applications About the MATLAB Runtime How is the MATLAB Runtime Different from MATLAB? Performance Considerations and the MATLAB Runtime	3-2 3-3 3-3
Distribute Integrated Java Applicat Package Java Applications	3-2 3-3 3-3 3-4 3-5
Package Java Applications About the MATLAB Runtime How is the MATLAB Runtime Different from MATLAB? Performance Considerations and the MATLAB Runtime Install and Configure the MATLAB Runtime Download the MATLAB Runtime Installer from the Web	3-2 3-3 3-3 3-4 3-5 3-5
Package Java Applications About the MATLAB Runtime How is the MATLAB Runtime Different from MATLAB? Performance Considerations and the MATLAB Runtime Install and Configure the MATLAB Runtime Download the MATLAB Runtime Installer from the Web Install the MATLAB Runtime Interactively	3-2 3-3 3-3 3-4 3-5 3-5 3-5
Package Java Applications About the MATLAB Runtime How is the MATLAB Runtime Different from MATLAB? Performance Considerations and the MATLAB Runtime Install and Configure the MATLAB Runtime Download the MATLAB Runtime Installer from the Web Install the MATLAB Runtime Interactively Install the MATLAB Runtime Non-Interactively	3-2 3-3 3-3 3-4 3-5 3-5 3-5 3-7
Package Java Applications About the MATLAB Runtime How is the MATLAB Runtime Different from MATLAB? Performance Considerations and the MATLAB Runtime Install and Configure the MATLAB Runtime Download the MATLAB Runtime Installer from the Web Install the MATLAB Runtime Interactively Install the MATLAB Runtime Non-Interactively Install the MATLAB Runtime without Administrator Rights	3-2 3-3 3-3 3-4 3-5 3-5 3-7 3-9
Package Java Applications About the MATLAB Runtime How is the MATLAB Runtime Different from MATLAB? Performance Considerations and the MATLAB Runtime Install and Configure the MATLAB Runtime Download the MATLAB Runtime Installer from the Web Install the MATLAB Runtime Interactively Install the MATLAB Runtime Non-Interactively Install the MATLAB Runtime without Administrator Rights Multiple MATLAB Runtime Versions on Single Machine	3-2 3-3 3-3 3-4 3-5 3-5 3-7 3-9 3-9
Package Java Applications About the MATLAB Runtime How is the MATLAB Runtime Different from MATLAB? Performance Considerations and the MATLAB Runtime Install and Configure the MATLAB Runtime Download the MATLAB Runtime Installer from the Web Install the MATLAB Runtime Interactively Install the MATLAB Runtime Non-Interactively Install the MATLAB Runtime without Administrator Rights Multiple MATLAB Runtime Versions on Single Machine MATLAB and MATLAB Runtime on Same Machine	3-2 3-3 3-3 3-4 3-5 3-5 3-7 3-9 3-9 3-10
Package Java Applications About the MATLAB Runtime How is the MATLAB Runtime Different from MATLAB? Performance Considerations and the MATLAB Runtime Install and Configure the MATLAB Runtime Download the MATLAB Runtime Installer from the Web Install the MATLAB Runtime Interactively Install the MATLAB Runtime Non-Interactively Install the MATLAB Runtime without Administrator Rights Multiple MATLAB Runtime Versions on Single Machine	3-2 3-3 3-3 3-4 3-5 3-5 3-7 3-9 3-9

D	is	tri	bute	tο	Fnd	Πs	ers
L	41.5	LLL	Dute	1.47			

1	ı

	AB Runtime Path Settings for Development and Testing
Pa W Li	ath for Java Development on All Platforms ath Modifications Required for Accessibility indows Settings for Development and Testing nux Settings for Development and Testing S X Settings for Development and Testing
MATLA	AB Runtime Path Settings for Run-Time Deployment
G	eneral Path Guidelines
	ath for Java Applications on All Platforms
	"indows Path for Run-Time Deployment
	nux Paths for Run-Time Deployment
	y a MATLAB Plot in a Java Application
- Pı	y a MATLAB Plot in a Java Application
Pr Pr Create	rocedure
Pı Pı Create Pı	arpose
Pı Pı Create Pı	rocedure
Pi Pi Create Pi Pi Matrix	arpose a Java Application with Two MATLAB Functions arpose rocedure Math
Pi Pi Create Pi Pi Matrix	arpose a Java Application with Two MATLAB Functions arpose cocedure Math arpose
Pi Pi Create Pi Pi Matrix Pi M	arpose cocedure a Java Application with Two MATLAB Functions cocedure cocedure Math curpose ATLAB Functions to Be Encapsulated
Pi Pr Create Pr Pr Matrix M U	arpose a Java Application with Two MATLAB Functions arpose cocedure Math arpose ATLAB Functions to Be Encapsulated anderstanding the getfactor Program
Pi Pi Create Pi Pi Matrix M U	arpose cocedure a Java Application with Two MATLAB Functions cocedure cocedure Math curpose ATLAB Functions to Be Encapsulated
Pi Pri Create Pi Pri Matrix U Pri	arpose a Java Application with Two MATLAB Functions arpose cocedure Math arpose ATLAB Functions to Be Encapsulated anderstanding the getfactor Program
Propered Property Pro	a Java Application with Two MATLAB Functions procedure Tocedure Math prose ATLAB Functions to Be Encapsulated procedure moderstanding the getfactor Program procedure

Purpose	5-27 5-27 5-28 5-20
Procedure Display a MATLAB Plot on the Web using a Java Servlet Overview Prerequisites Locating and Copying the Example Files Build Your Java Package Compiling Your Java Code Generating the Web Archive (WAR) File Running the Web Deployment Example Using the Web Application	5-29 5-37 5-37 5-38 5-39 5-40 5-40
Working with MATLAB Figures and Important Roles in Working with Figures and Images	ages 6-2 6-3
For More Comprehensive Examples	6-3 6-3
Creating Scalable Web Applications Using	RMI
Use Remote Method Invocation (RMI)	7-2
RMI Prerequisites Ensure You Have the Required Products Ensure Your Web Server Is Java Compliant Install the javabuilder.jar Library	7-3 7-3 7-3 7-3
Run Client and Server on Same Machine	7-4

Run Client and Server on Separate Machines	
Why Use Native Cell Arrays and Struct Arrays? Using Native Types Does Not Require a Client-Side MATLAB	
Runtime	
Native Data Marshaling Prerequisites	7
Use Native Java Cell and Struct Arrays	7
Before You Run the Example	7
Running the Example	7
Additional RMI Examples	7
Troubleshoo	t
Common MATLAB Compiler SDK Error Messages	
Common MATLAB Compiler SDK Error Messages	
Common MATLAB Compiler SDK Error Messages	
Common MATLAB Compiler SDK Error Messages	
Common MATLAB Compiler SDK Error Messages	Jä
	Já
	Já
Reference Information for	Jā
Reference Information for Requirements for the MATLAB Compiler SDK Java Target	J
Reference Information for Requirements for the MATLAB Compiler SDK Java Target System Requirements	Jä
Reference Information for Requirements for the MATLAB Compiler SDK Java Target System Requirements	Jä
Reference Information for Requirements for the MATLAB Compiler SDK Java Target System Requirements	Jä
Reference Information for Requirements for the MATLAB Compiler SDK Java Target System Requirements	Já
Reference Information for Requirements for the MATLAB Compiler SDK Java Target System Requirements	Jä
Requirements for the MATLAB Compiler SDK Java Target System Requirements Path Modifications Required for Accessibility Limitations of the MATLAB Compiler SDK Java Target Rules for Data Conversion Between Java and MATLAB Java to MATLAB Conversion MATLAB to Java Conversion Unsupported MATLAB Array Types Programming Interfaces Generated MATLAB Compiler SDK	J
Requirements for the MATLAB Compiler SDK Java Target System Requirements Path Modifications Required for Accessibility Limitations of the MATLAB Compiler SDK Java Target Rules for Data Conversion Between Java and MATLAB Java to MATLAB Conversion MATLAB to Java Conversion Unsupported MATLAB Array Types Programming Interfaces Generated MATLAB Compiler SDK	Jā
Requirements for the MATLAB Compiler SDK Java Target System Requirements Path Modifications Required for Accessibility Limitations of the MATLAB Compiler SDK Java Target Rules for Data Conversion Between Java and MATLAB Java to MATLAB Conversion MATLAB to Java Conversion Unsupported MATLAB Array Types Programming Interfaces Generated MATLAB Compiler SDK APIs Based on MATLAB Function Signatures	J
Requirements for the MATLAB Compiler SDK Java Target System Requirements Path Modifications Required for Accessibility Limitations of the MATLAB Compiler SDK Java Target Rules for Data Conversion Between Java and MATLAB Java to MATLAB Conversion MATLAB to Java Conversion Unsupported MATLAB Array Types Programming Interfaces Generated MATLAB Compiler SDK	<u> </u>

Share MA	ATLAB Runtime Instances
What	t Is a Singleton MATLAB Runtime?
Adva	antages and Disadvantages of Using a Singleton
MWArray	Class Specification

Functions — Alphabetical List

10

Overview

- "Product Overview" on page 1-2
- "Configure Your Java Environment" on page 1-3

Product Overview

In this section...

"How Does Java Package Deployment Work?" on page 1-2

"Limitations of Support" on page 1-2

How Does Java Package Deployment Work?

There are two kinds of deployment:

- Installing the generated packages and setting up support for them on a development machine so that they can be accessed by a developer who seeks to use them in writing a Java application.
- Deploying support for the generated packages when they are accessed at run time on an end user machine.

To accomplish this kind of deployment, you must make sure that the installer you create for the application takes care of supporting the Java packages on the target machine. In general, this means the MATLAB Runtime must be installed, on the target machine. You must also install the compiler generated packages.

Note Java packages created with the MATLAB Compiler SDK product are dependent on the version of MATLAB with which they were built.

Limitations of Support

MATLAB Compiler SDK provides a wide variety of support for various Java types and objects. However, MATLAB objects are not supported as inputs or outputs for compiled or deployed functions.

Configure Your Java Environment

In this section...

"Install the Required JDK" on page 1-3

"Set JAVA HOME" on page 1-4

"Set the CLASSPATH" on page 1-4

"Configure the Native Library Path Variables" on page 1-5

Before you can use the generated Java packages in a Java development environment, you need to ensure that your Java environment is properly configured. You must verify that:

- Your system uses a version of the Java Developer's Kit (JDK™) that is compatible with MATLAB.
- JAVA_HOME is set to the folder containing the system's JDK installation.
- CLASSPATH contains all of the MATLAB library JAR files and the JAR files for the packages containing your compiled MATLAB code.
- The MATLAB native library paths are properly configured.

Note For updated Java system requirements, including versions of Java Developer's Kit (JDK) and Java Runtime Environment (JRE™), see the supported compiler page at https://www.mathworks.com/support/compilers/current_release/.

Install the Required JDK

To install the proper version of the JDK:

- **1** Verify the version of Java your MATLAB installation is using by running the following MATLAB command:
 - version java
- **2** Download a Java Developer's Kit (JDK) with the same major version from https://adoptopenjdk.net/.
- **3** Install the JDK.

Note If you are not developing applications or compiling MATLAB code, you can use the Java Runtime Environment (JRE) instead of the JDK.

Set JAVA_HOME

- **1** From the system command prompt, set the system environment variable, JAVA HOME, to point to your JDK installation.
 - For example on Windows® enter set JAVA HOME=path to Java install.
- 2 If you are compiling MATLAB code, verify that MATLAB is reading the correct value of JAVA HOME.
 - At the MATLAB command prompt, type getenv JAVA_HOME to display the value of JAVA HOME in use by MATLAB.
- **3** Verify that the folder containing your Java installation has been added to your system PATH environment variable.

For example on Windows enter set PATH=%PATH%; path to Java install.

Set the CLASSPATH

To build and run a Java application that uses a MATLAB Compiler SDK generated component, the system must locate:

- JAR files containing the MATLAB libraries
- Packages that you have developed and built

Java classes compiled with MATLAB Compiler SDK use classes contained in the com.mathworks.toolbox.javabuilder package. To use the compiled classes, you need to include a file called javabuilder.jar on the Java class path. You can find this file in one of the following folders:

MATLAB installed on your system matlabroot/toolbox/

javabuilder/jar

MATLAB Runtime installed on your system <code>mcrroot/toolbox/javabuilder/jar</code>

Note *matlabroot* refers to the root folder into which the MATLAB installer has placed the MATLAB files. *mcrroot* refers to the root folder under which MATLAB Runtime is installed.

In addition, you need to add to the JAR files created by the compiler to the class path.

Configure the Native Library Path Variables

The operating system uses the native library path to locate native libraries that are needed to run your Java class. See the following list of variable names according to operating system:

Windows PATH

Linux® LD_LIBRARY_PATH
Macintosh DYLD LIBRARY PATH

The native MATLAB or MATLAB Runtime files needed to execute the compiled MATLAB functions called from the Java code must be included on the paths listed by your system's native library path variable.

Programming

- "MATLAB Compiler SDK and the JVM" on page 2-2
- "Integrate a Java Package into an Application" on page 2-3
- "About the MATLAB Compiler SDK Java API" on page 2-8
- "Pass Arguments To and From Java" on page 2-13
- "Pass Java Objects by Reference" on page 2-25
- "Use Multiple Packages in Single Application" on page 2-30
- "Error Handling" on page 2-35
- "Manage MATLAB Resources" on page 2-41
- "MATLAB Runtime User Data Interface" on page 2-44
- "Supply Run-Time Profile Information for Parallel Computing Toolbox Applications" on page 2-45
- "Dynamically Specify Options to the MATLAB Runtime" on page 2-50
- "Data Conversion Between Java and MATLAB" on page 2-53
- "Set Java Properties" on page 2-55
- "Execution of Applications that Create Figures" on page 2-57
- "Ensuring Multi-Platform Portability" on page 2-59
- "Deployable Archive Embedding and Extraction" on page 2-61
- "Explore the Javadoc" on page 2-65

Note For examples of these tasks, see the sample Java applications in this documentation.

For information about deploying your application after you complete these tasks, see "How Does Java Package Deployment Work?" on page 1-2.

MATLAB Compiler SDK and the JVM

Packages produced by MATLAB Compiler SDK use Java Native Interface (JNI) to interact with the MATLAB Runtime.

When the first MATLAB Compiler SDK object is instantiated:

- 1 Dependent MATLAB Compiler SDK classes are loaded.
- **2** A series of shared libraries forming the JNI bridge from the generated package to the MATLAB Runtime are loaded.
- 3 The MATLAB Runtime is initialized by creating an instance of a C++ class called mcrInstance.
- **4** The MATLAB-Java interface establishes a connection to the JVM[™] by calling the JNI method AttachCurrentThread.
- 5 AttachCurrentThread creates a class loader that loads all classes needed by MATLAB code utilizing the MATLAB-Java interface.
- The MATLAB Runtime C++ core allocates resources for the arrays created by the Java API.

As you create MWArray objects to interact with the MATLAB Runtime, the JVM creates a wrapper object for the MATLAB mxArray object. The MATLAB Runtime C++ core allocates the actual resources to store the mxArray object. This has an impact on how the JVM frees up resources used by your application. Most of the resources used when interacting with MATLAB are created by the MATLAB Runtime C++ core. The JVM only knows about the MATLAB resources through the JNI wrappers created for them. Because of this, the JVM does not know the size of the resources being consumed and cannot effectively manage them using its built in garbage collector. The JVM also does not manage the threads used by the MATLAB Runtime and cannot clean them up.

All of the MATLAB Compiler SDK classes have static methods to properly dispose of their resources. The disposal methods trigger the freeing of the underlying resources in the MATLAB Runtime C++ core. Not properly disposing of MATLAB Compiler SDK objects can result in unpredictable behavior and may look like your application has a memory leak.

Integrate a Java Package into an Application

This example shows how to invoke a MATLAB generated method in a Java application.

To create a Java application that calls a MATLAB generated method:

- **1** Install the MATLAB Runtime and generated JAR files in one of the following ways:
 - Run the installer generated by MATLAB. It is located in the for redistributionfolder of the deployment project.

Doing so automatically installs the MATLAB Runtime from the web and places the generated JAR files onto your computer.

 Manually install the MATLAB Runtime and the generated JAR files onto your development system.

You can download the MATLAB Runtime installer from https://www.mathworks.com/products/compiler/mcr. The generated JAR files are located in the MATLAB deployment project's for_testing folder.

- 2 In the folder containing the generated JAR files, create a new file called getmagic.java.
- **3** Using a text editor, open getmagic.java.
- **4** Place the following as the first line in the file.

```
import com.mathworks.toolbox.javabuilder.*;
```

This statement imports the MATLAB support classes.

5 Place the following line after the first import statement.

```
import makesqr.*;
```

This statement imports the classes generated by the compiler.

6 Add the following class definition.

```
class getmagic
{
}
```

This class has a single main method that calls the generated class.

7 Add the main() method to the application.

```
public static void main(String[] args)
{
}
```

8 Add the following code to the top of the main() method.

```
MWNumericArray n = null;
Object[] result = null;
Class1 theMagic = null;
```

This initializes the variables used by the application.

- *n* is an instance of the MATLAB MWNumericArray class that MATLAB uses for its internal data format.
- result is a generic Java object that holds the results of the call to MATLAB.
- *theMagic* is an instance class generated from the MATLAB function.
- **9** Add the following code after the variable initialization.

```
if (args.length == 0)
{
   System.out.println("Error: must input a positive integer");
   return;
}
```

This is a simple check to ensure that the required command-line argument was passed to the application.

- **10** Add a try/catch/finally block after the argument check.
- 11 In the try section of the try/catch/finally block, add the following code.

```
n = new MWNumericArray(Double.valueOf(args[0]), MWClassID.DOUBLE);
```

The code instantiates an instance of MWNumericArray and populates it with a 1-by-1 array containing the integer passed to the application on the command line. The value is converted to a <code>Double</code> because that is the most direct mapping between the Java and MATLAB internal data representation.

12 After the code instantiating the input parameter, add the following to instantiate the class generated from MATLAB.

```
theMagic = new Class1();
```

The constructor for the generated class handles all of the setup required to start the MATLAB Runtime and populate it with the required MATLAB code.

13 Using the newly instantiated object, call the MATLAB function.

```
result = theMagic.makesgr(1, n);
    System.out.println(result[0]);
14 Add the following catch section to the try/catch/finally block to handle any
    exceptions that might be thrown.
    catch (Exception e)
      System.out.println("Exception: " + e.toString());
15 Add the following finally section to the try/catch/finally block to clean up any
    resources.
    finally
     MWArray.disposeArray(n);
     MWArray.disposeArray(result);
      theMagic.dispose();
    }
    The disposeArray() and dispose() methods clean up the resources used by the
    generated MATLAB code.
16 Save the Java file.
    The completed Java file should resemble the following.
    import com.mathworks.toolbox.javabuilder.*;
    import makesqr.*;
    class getmagic
       public static void main(String[] args)
          MWNumericArray n = null;
          Object[] result = null;
          Class1 theMagic = null;
          if (args.length == 0)
            System.out.println("Error: must input a positive integer");
            return;
          }
```

try

- **17** Use the system's command line to navigate to the folder where you installed the generated Java package and saved the new Java file.
- Compile the Java application using javac.

Note Enter the javac command on a single line.

On $UNIX^{\otimes}$ platforms, use colon (:) as the class path delimiter instead of semicolon (;).

mcrroot is the path to where the MATLAB Runtime is installed on your system. If you have MATLAB installed on your system instead, you can use the path to your MATLAB installation.

From the system's command prompt, run the application.

```
java -classpath .;"mcrroot\toolbox\javabuilder\jar\javabuilder.jar";
     .\makesqr.jar getmagic 5
    17
          24
                        8
                             15
                 1
    23
           5
                 7
                       14
                             16
     4
           6
                 13
                       20
                             22
```

10	12	19	21	3
11	18	25	2	9

You must be sure to place a dot (.) in the first position of the class path. If it not, you get a message stating that Java cannot load the class.

Note Enter the java command on a single line.

On UNIX platforms, use colon (:) as the class path delimiter instead of semicolon (;).

mcrroot is the path to where the MATLAB Runtime is installed on your system. If you have MATLAB installed on your system instead, you can use the path to your MATLAB installation.

To follow up on this example:

- Try installing the new application on a different computer.
- Try building an installer for the application.
- Try integrating a package that consists of multiple functions.

About the MATLAB Compiler SDK Java API

In this section...

"What Are MATLAB Generated Java Packages and When Should You Create Them?" on page 2-8

"Understanding the MATLAB Compiler SDK Java API Data Conversion Classes" on page 2-8

"Automatic Conversion to MATLAB Types" on page 2-10

"Understanding Function Signatures Generated by the MATLAB Compiler SDK Product" on page 2-10

"Adding Fields to Data Structures and Data Structure Arrays" on page 2-11

"Returning Data from MATLAB to Java" on page 2-12

What Are MATLAB Generated Java Packages and When Should You Create Them?

MATLAB generated Java packages include one or more Java classes that wrap your MATLAB functions. The classes provide methods that allow you to call the functions as you would any other Java method. In addition, the generated classes provide all of the functionality required to manage the MATLAB Runtime required to run the MATLAB functions.

The compiler encrypts your MATLAB functions and generates a Java wrapper around them so that they behave just like any other Java class. You can deploy generated packages to enterprise or Web environments, sharing them with anyone running a Web browser and having the MATLAB Runtime installed.

For development on Linux platforms, Java packages and applications provide portable and scalable solutions for applications in large-scale enterprise or Web environments.

Understanding the MATLAB Compiler SDK Java API Data Conversion Classes

When writing your Java application, you can represent your data using objects of any of the data conversion classes. Alternatively, you can use standard Java data types and objects. The data conversion classes are built as a class hierarchy that represents the major MATLAB array types.

Note This discussion provides conceptual information about the classes. For details, see com.mathworks.toolbox.javabuilder.

This discussion assumes you have a working knowledge of the Java programming language and the Java Software Developer's Kit (SDK). This is not intended to be a discussion on how to program in Java. Refer to the documentation that came with your Java SDK for general programming information.

Overview of Classes and Methods in the Data Conversion Class Hierarchy

The root of the data conversion class hierarchy is the MWArray abstract class. The MWArray class has the following subclasses representing the major MATLAB types: MWNumericArray, MWLogicalArray, MWCharArray, MWCellArray, and MWStructArray.

Each subclass stores a reference to a native MATLAB array of that type. Each class provides constructors and a basic set of methods for accessing the underlying array's properties and data. To be specific, MWArray and the classes derived from MWArray provide the following:

- Constructors and finalizers to instantiate and dispose of MATLAB arrays
- get and set methods to read and write the array data
- Methods to identify properties of the array
- · Comparison methods to test the equality or order of the array
- Conversion methods to convert to other data types

Advantage of Using Data Conversion Classes

The MWArray data conversion classes let you pass native type parameters directly without using explicit data conversion. If you pass the same array frequently, you might improve the performance of your program by storing the array in an instance of one of the MWArray subclasses.

Automatic Conversion to MATLAB Types

Note Because the conversion process is automatic (in most cases), you do not need to understand the conversion process to pass and return arguments with MATLAB Compiler SDK generated methods.

When you pass an MWArray instance as an input argument, the encapsulated MATLAB array is passed directly to the method being called.

In contrast, if your code uses a native Java primitive or array as an input parameter, the compiler converts it to an instance of the appropriate MWArray class before it is passed to the method. The compiler can convert any Java string, numeric type, or any multidimensional array of these types to an appropriate MWArray type, using its data conversion rules. See "Rules for Data Conversion Between Java and MATLAB" on page 9-4 for a list of all the data types that are supported along with their equivalent types in MATLAB.

The conversion rules apply not only when calling your own methods, but also when calling constructors and factory methods belonging to the MWArray classes.

Note To work directly with cell arrays and data structures in native Java, see "Use Native Java Cell and Struct Arrays" on page 7-12 for information and comprehensive examples.

Understanding Function Signatures Generated by the MATLAB Compiler SDK Product

The Java programming language now supports optional function arguments in the way that MATLAB does with varargin and varargout. To support this feature of MATLAB, the compiler generates a single overloaded Java method that accommodates any number of input arguments. This behavior is an enhancement over previous versions of varargin support that only handled a limited number of arguments.

Note In addition to handling optional function arguments, the overloaded Java methods that wrap MATLAB functions handle data conversion. See "Automatic Conversion to MATLAB Types" on page 2-10 for more details.

Understanding MATLAB Function Signatures

As background, recall that the generic MATLAB function has the following structure:

To the *left* of the equal sign, the function specifies a set of explicit and optional return arguments.

To the *right* of the equal sign, the function lists explicit *input* arguments followed by one or more optional arguments.

Each argument represents a MATLAB type. When you include the varargin or varargout argument, you can specify any number of inputs or outputs beyond the ones that are explicitly declared.

Overloaded Methods in Java That Encapsulate MATLAB Code

When the MATLAB Compiler SDK product encapsulates your MATLAB code, it creates an overloaded method that implements the MATLAB functions. This overloaded method corresponds to a call to the generic MATLAB function for each combination of the possible number and type of input arguments.

In addition to encapsulating input arguments, the compiler creates another method, which represents the output arguments, or return values, of the MATLAB function. This additional overloaded method takes care of return values for the encapsulated MATLAB function. This method of encapsulating the information about return values simulates the mlx interface generated for the C/C++ MATLAB Compiler SDK target.

These overloaded methods are called the standard interface and the mlx interface. See "Programming Interfaces Generated MATLAB Compiler SDK" on page 9-9 for details.

Adding Fields to Data Structures and Data Structure Arrays

When adding fields to data structures and data structure arrays, do so using standard programming techniques. Do not use the set command as a shortcut.

Returning Data from MATLAB to Java

All data returned from a method coded in MATLAB is passed as an instance of the appropriate MWArray subclass. For example, a MATLAB cell array is returned to the Java application as an MWCellArray object.

Return data is *not* converted to a Java type. If you choose to use a Java type, you must convert to that type using the toArray method of the MWArray subclass to which the return data belongs.

Note To work directly with cell arrays and data structures in native Java, see "Use Native Java Cell and Struct Arrays" on page 7-12 for information and comprehensive examples.

Pass Arguments To and From Java

In this section...

"Format" on page 2-13

"Manual Conversion of Data Types" on page 2-13

"Automatic Conversion to a MATLAB Type" on page 2-14

"Specify Optional Arguments" on page 2-16

"Handle Return Values" on page 2-20

Format

When you invoke a method on a generated class, the input arguments received by the method must be in the MATLAB internal array format. You can either convert them yourself within the calling program, or pass the arguments as Java data types, which are then automatically converted by the calling mechanism.

To convert them yourself, use instances of the MWArray classes; in this case you are using manual conversion. Storing your data using the classes and data types defined in the Java language means that you are relying on automatic conversion. Most likely, you will use a combination of manual and automatic conversion.

Manual Conversion of Data Types

To manually convert to one of the standard MATLAB data types, use the MWArray data conversion classes provided by the compiler. For class reference and usage information, see the com.mathworks.toolbox.javabuilder package.

Using MWNumericArray

The Magic Square example ("Integrate a Java Package into an Application" on page 2-3) exemplifies manual conversion. The following code fragment from that program shows a java.lang.Double argument that is converted to an MWNumericArray type that can be used by the MATLAB function without further conversion:

```
result = theMagic.makesqr(1, n);
```

Passing an MWArray

This example constructs an MWNumericArray of type MWClassID.DOUBLE. The call to myprimes passes the number of outputs, 1, and the MWNumericArray, x:

```
x = new MWNumericArray(n, MWClassID.DOUBLE);
cls = new myclass();
y = cls.myprimes(1, x);
```

The Java bridge converts the MWNumericArray object to a MATLAB scalar double to pass to the MATLAB function.

Automatic Conversion to a MATLAB Type

When passing an argument only a small number of times, it is usually just as efficient to pass a primitive Java type or object. In this case, the calling mechanism converts the data for you into an equivalent MATLAB type.

For instance, either of the following Java types would be automatically converted to the MATLAB double type:

- A Java double primitive
- An object of class java.lang.Double

For reference information about data conversion (tables showing each Java type along with its converted MATLAB type, and each MATLAB type with its converted Java type), see "Rules for Data Conversion Between Java and MATLAB" on page 9-4.

Automatic Data Conversion

When calling the makesqr method used in the getmagic application, you could construct an object of type MWNumericArray. Doing so would be an example of manual conversion. Instead, you could rely on automatic conversion, as shown in the following code fragment:

```
result = M.makesqr(1, arg[0]);
```

In this case, a Java double is passed as arg[0].

Here is another example:

```
result = theFourier.plotfft(3, data, new Double(interval));
```

In this Java statement, the third argument is of type <code>java.lang.Double</code>. According to conversion rules, the <code>java.lang.Double</code> automatically converts to a MATLAB 1-by-1 double array.

Passing a Java Double Object

The example calls the myprimes method with two arguments. The first specifies the number of arguments to return. The second is an object of class java.lang.Double that passes the one data input to myprimes.

```
cls = new myclass();
y = cls.myprimes(1, new Double((double)n));
```

This second argument is converted to a MATLAB 1-by-1 double array, as required by the MATLAB function. This is the default conversion rule for java.lang.Double.

Passing an MWArray

This example constructs an MWNumericArray of type MWClassID.DOUBLE. The call to myprimes passes the number of outputs, 1, and the MWNumericArray, x.

```
x = new MWNumericArray(n, MWClassID.DOUBLE);
cls = new myclass();
y = cls.myprimes(1, x);
```

The compiler converts the MWNumericArray object to a MATLAB scalar double to pass to the MATLAB function.

Calling MWArray Methods

The conversion rules apply not only when calling your own methods, but also when calling constructors and factory methods belonging to the MWArray classes.

For example, the following code fragment calls the constructor for the MWNumericArray class with a Java double as the input argument:

```
double Adata = 24;
MWNumericArray A = new MWnumericArray(Adata);
System.out.println("Array A is of type " + A.classID());
```

The compiler converts the input argument to an instance of MWNumericArray, with a ClassID property of MWClassID.DOUBLE. This MWNumericArray object is the equivalent of a MATLAB 1-by-1 double array.

When you run this example, the result is as follows:

```
Array A is of type double
```

Changing the Default by Specifying the Type

When calling an MWArray class method constructor, supplying a specific data type causes the MATLAB Compiler SDK product to convert to that type instead of the default.

For example, in the following code fragment, the code specifies that A should be constructed as a MATLAB 1-by-1 16-bit integer array:

```
double Adata = 24;
MWNumericArray A = new MWnumericArray(Adata, MWClassID.INT16);
System.out.println("Array A is of type " + A.classID());
```

When you run this example, the result is as follows:

```
Array A is of type int16
```

Specify Optional Arguments

So far, the examples have not used MATLAB functions that have varargin or varargout arguments. Consider the following MATLAB function:

```
function y = mysum(varargin)
y = sum([varargin{:}]);
```

This function returns the sum of the inputs. The inputs are provided as a varargin argument, which means that the caller can specify any number of inputs to the function. The result is returned as a scalar double.

Pass Variable Numbers of Inputs

The MATLAB Compiler SDK product generates a Java interface to this function as follows:

```
/* mlx interface - List version*/
public void mysum(List lhs, List rhs)
```

```
throws MWException
{
   (implementation omitted)
/* mlx interface - Array version*/
public void mysum(Object[] lhs, Object[] rhs)
                          throws MWException
{
   (implementation omitted)
}
/* standard interface - no inputs */
public Object[] mysum(int nargout) throws MWException
   (implementation omitted)
}
/* standard interface - variable inputs */
public Object[] mysum(int nargout, Object varargin)
                          throws MWException
{
   (implementation omitted)
}
```

In all cases, the varargin argument is passed as type <code>Object</code>. This lets you provide any number of inputs in the form of an array of Object, that is <code>Object[]</code>, and the contents of this array are passed to the compiled MATLAB function in the order in which they appear in the array. Here is an example of how you might use the <code>mysum</code> method in a Java program:

```
public double getsum(double[] vals) throws MWException
{
    myclass cls = null;
    Object[] x = {vals};
    Object[] y = null;

    try
    {
        cls = new myclass();
        y = cls.mysum(1, x);
        return ((MWNumericArray)y[0]).getDouble(1);
    }

    finally
```

```
{
    MWArray.disposeArray(y);
    if (cls != null)
        cls.dispose();
    }
}
```

In this example, an Object array of length 1 is created and initialized with a reference to the supplied double array. This argument is passed to the mysum method. The result is known to be a scalar double, so the code returns this double value with the statement:

```
return ((MWNumericArray)y[0]).getDouble(1);
```

Cast the return value to MWNumericArray and invoke the getDouble(int) method to return the first element in the array as a primitive double value.

Pass Array Inputs

The next example performs a more general calculation:

```
public double getsum(Object[] vals) throws MWException
   myclass cls = null;
   Object[] x = null;
   Object[] y = null;
   try
      x = new Object[vals.length];
      for (int i = 0; i < vals.length; i++)
         x[i] = new MWNumericArray(vals[i], MWClassID.DOUBLE);
      cls = new myclass();
      y = cls.mysum(1, x);
      return ((MWNumericArray)y[0]).getDouble(1);
   }
   finally
      MWArray.disposeArray(x);
      MWArray.disposeArray(y);
      if (cls != null)
         cls.dispose();
   }
}
```

This version of getsum takes an array of Object as input and converts each value to a double array. The list of double arrays is then passed to the mysum function, where it calculates the total sum of each input array.

Pass a Variable Number of Outputs

When present, varargout arguments are handled in the same way that varargin arguments are handled. Consider the following MATLAB function:

```
function varargout = randvectors
for i=1:nargout
   varargout{i} = rand(1, i);
end
```

This function returns a list of random double vectors such that the length of the ith vector is equal to i. The MATLAB Compiler™ product generates a Java interface to this function as follows:

Pass Optional Arguments with the Standard Interface

Object[] v = null;

Here is one way to use the randvectors method in a Java program:
public double[][] getrandvectors(int n) throws MWException
{
 mvclass cls = null:

```
2-19
```

```
try
{
    cls = new myclass();
    y = cls.randvectors(n);
    double[][] ret = new double[y.length][];

    for (int i = 0; i < y.length; i++)
        ret[i] = (double[])((MWArray)y[i]).getData();
    return ret;
}

finally
{
    MWArray.disposeArray(y);
    if (cls != null)
        cls.dispose();
}
</pre>
```

The getrandvectors method returns a two-dimensional double array with a triangular structure. The length of the ith row equals i. Such arrays are commonly referred to as jagged arrays. Jagged arrays are easily supported in Java because a Java matrix is just an array of arrays.

Handle Return Values

The previous examples used the fact that you knew the type and dimensionality of the output argument. In the case that this information is unknown, or can vary (as is possible in MATLAB programming), the code that calls the method might need to query the type and dimensionality of the output arguments.

There are several ways to do this. Do one of the following:

- Use reflection support in the Java language to query any object for its type.
- Use several methods provided by the MWArray class to query information about the underlying MATLAB array.
- Coercing to a specific type using the to Type Array methods.

Use Java Reflection to Determine Type and Dimensionality

This code sample calls the myprimes method, and then determines the type using reflection. The example assumes that the output is returned as a numeric matrix but the exact numeric type is unknown.

```
public void getprimes(int n) throws MWException
   myclass cls = null;
   Object[] y = null;
   try
   {
      cls = new myclass();
      y = cls.myprimes(1, new Double((double)n));
      Object a = ((MWArray)y[0]).toArray();
      if (a instanceof double[][])
      {
         double[][] x = (double[][])a;
         /* (do something with x...) */
      }
      else if (a instanceof float[][])
         float[][] x = (float[][])a;
         /* (do something with x...) */
      }
      else if (a instanceof int[][])
      {
         int[][] x = (int[][])a;
         /* (do something with x...) */
      }
      else if (a instanceof long[][])
         long[][] x = (long[][])a;
         /* (do something with x...) */
      }
```

```
else if (a instanceof short[][])
{
    short[][] x = (short[][])a;

    /* (do something with x...) */
}
else if (a instanceof byte[][])
{
    byte[][] x = (byte[][])a;

    /* (do something with x...) */
}
else
{
    throw new MWException(
        "Bad type returned from myprimes");
}
```

This example uses the toArray method to return a Java primitive array representing the underlying MATLAB array. The toArray method works just like getData in the previous examples, except that the returned array has the same dimensionality as the underlying MATLAB array.

Use MWArray Query to Determine Type and Dimensionality

The next example uses the MWArray classID method to determine the type of the underlying MATLAB array. It also checks the dimensionality by calling numberOfDimensions. If any unexpected information is returned, an exception is thrown. It then checks the MWClassID and processes the array accordingly.

```
public void getprimes(int n) throws MWException
{
    myclass cls = null;
    Object[] y = null;

    try
    {
       cls = new myclass();
       y = cls.myprimes(1, new Double((double)n));
       MWClassID clsid = ((MWArray)y[0]).classID();
}
```

```
if (!clsid.isNumeric() ||
   ((MWArray)y[0]).numberOfDimensions() != 2)
{
   throw new MWException("Bad type
                    returned from myprimes");
}
if (clsid == MWClassID.DOUBLE)
   double[][] x = (double[][])((MWArray)y[0]).toArray();
   /* (do something with x...) */
}
else if (clsid == MWClassID.SINGLE)
   float[][] x = (float[][])((MWArray)y[0]).toArray();
   /* (do something with x...) */
}
else if (clsid == MWClassID.INT32 ||
        clsid == MWClassID.UINT32)
   int[][] \times = (int[][])((MWArray)y[0]).toArray();
   /* (do something with x...) */
}
else if (clsid == MWClassID.INT64 ||
        clsid == MWClassID.UINT64)
{
   long[][] x = (long[][])((MWArray)y[0]).toArray();
   /* (do something with x...) */
}
else if (clsid == MWClassID.INT16 ||
        clsid == MWClassID.UINT16)
{
   short[][] x = (short[][])((MWArray)y[0]).toArray();
  /* (do something with x...) */
```

Use to Type Array Methods to Determine Type and Dimensionality

The next example demonstrates how you can coerce or force data to a specified numeric type by invoking any of the to Type Array methods. These methods return an array of Java elements of the type specified in the name of the called method. The data is coerced or forced to the primitive type specified in the method name. Note that when using these methods, data will be truncated when needed to allow conformance to the specified data type.

```
Object results = null;
try {
    // call a compiled MATLAB function
    results = myobject.myfunction(2);

    // first output is known to be a numeric matrix
    MWArray resultA = (MWNumericArray) results[0];
    double[][] a = (double[][]) resultA.toDoubleArray();

    // second output is known to be
    // a 3-dimensional numeric array
    MWArray resultB = (MWNumericArray) results[1];
    int[][][] b = (int[][][]) resultB.toIntArray();
}
finally {
    MWArray.disposeArray(results);
}
```

Pass Java Objects by Reference

In this section... "MATLAB Array" on page 2-25 "Wrap and Pass Objects to MATLAB" on page 2-25

MATLAB Array

MWJavaObjectRef, a special subclass of MWArray, can be used to create a MATLAB array that references Java objects. For detailed usage information on this class, constructor, and associated methods, see the MWJavaObjectRef page in the Javadoc or search for MWJavaObjectRef in the MATLAB Help browser **Search** field.

You can find the Javadoc at matlabroot/help/javabuilder/MWArrayAPI in your product installation.

Wrap and Pass Objects to MATLAB

You can create a MATLAB code wrapper around Java objects using MWJavaObjectRef. Using this technique, you can pass objects by reference to MATLAB functions, clone a Java object inside a generated package, as well as perform other object marshaling specific to the MATLAB Compiler SDK product. The examples in this section present some common use cases.

Passing a Java Object into a MATLAB Compiler SDK Java Method

To pass an object into a MATLAB Compiler SDK Java method:

- 1 Use MWJavaObjectRef to wrap your object.
- **2** Pass your object to a MATLAB function. For example:

```
/* Pass it to a MATLAB function that lists its methods, etc */
result = theComponent.displayObj(1, origRef);
MWArray.disposeArray(origRef);
```

Cloning an Object

You can also use MWJavaObjectRef to clone an object. Continuing with the example in "Passing a Java Object into a MATLAB Compiler SDK Java Method" on page 2-25, do the following:

- **1** Add to the original hash.
- **2** Clone the object.
- **3** (Optional) Continue to add items to each copy. For example:

```
origRef = new MWJavaObjectRef(hash);
System.out.println("hash:");
System.out.println(hash.toString());
result = theComponent.addToHash(1, origRef);
outputRef = (MWJavaObjectRef)result[0];
/* We can typecheck that the reference contains a
/*
         Hashtable but not <String,Integer>;
/* this can cause issues if we get a Hashtable<wrong,wrong>. */
java.util.Hashtable<String, Integer> outHash =
          (java.util.Hashtable<String,Integer>)(outputRef.get());
/* We've added items to the original hash, cloned it, */
/* then added items to each copy */
System.out.println("hash:");
System.out.println(hash.toString());
System.out.println("outHash:");
System.out.println(outHash.toString());
```

For reference, here is the source code for addToHash.m:

addToHash.m

```
function h2 = addToHash(h)
% Validate input
if ~isa(h,'java.util.Hashtable')
    error('addToHash:IncorrectType', ...
        'addToHash expects a java.util.Hashtable');
end
% Add an item
h.put('From MATLAB',12);
% Clone the Hashtable and add items to both resulting objects
h2 = h.clone();
```

```
h.put('Orig',20);
h2.put('Clone',21);
```

Passing a Date into a Method and Getting a Date from a Method

In addition to passing in created objects, as in "Passing a Java Object into a MATLAB Compiler SDK Java Method" on page 2-25, you can also use MWJavaObjectRef to pass in Java utility objects such as java.util.date. To do so, perform the following steps:

- 1 Get the current date and time using the Java object java.util.date.
- 2 Create an instance of MWJavaObjectRef in which to wrap the Java object.
- Pass it to a MATLAB function that performs further processing, such as nextWeek.m. For example:

For reference, here is the source code for nextWeek.m:

nextWeek.m

```
function nextWeekDate = nextWeek(nowDate)
% Validate input
if ~isa(nowDate,'java.util.Date')
    error('nextWeekDate:IncorrectType', ...
        'nextWeekDate expects a java.util.Date');
end
% Use java.util.Calendar to calculate one week later
% than the supplied
% java.util.Date
cal = java.util.Calendar.getInstance();
cal.setTime(nowDate);
cal.add(java.util.Calendar.DAY_OF_MONTH, 7);
nextWeekDate = cal.getTime();
```

Returning Java Objects Using unwrapJavaObjectRefs

If you want actual Java objects returned from a method (without the MATLAB wrappering), use unwrapJavaObjectRefs.

This method recursively connects a single MWJavaObjectRef or a multidimensional array of MWJavaObjectRef objects to a reference or array of references.

The following code snippets show two examples of calling unwrapJavaObjectRefs:

Returning a Single Reference or Reference to an Array of Objects with unwrapJavaObjectRefs

Produces the following output:

```
A referenced the object: 12
B referenced the object: {b=5, a=3}
```

Returning an Array of References with unwrapJavaObjectRefs

Produces the following output:

refArr referenced the objects: 12 and 104

Optimization Example Using MWJavaObjectRef

For a full example of how to use MWJavaObjectRef to create a reference to a Java object and pass it to a method, see "Pass Java Objects to MATLAB" on page 5-27.

Use Multiple Packages in Single Application

```
In this section...

"Work with MATLAB Function Handles" on page 2-30

"Work with Objects" on page 2-32
```

When developing applications that use multiple MATLAB packages, consider that the following cannot be shared between assemblies:

- MATLAB function handles
- MATLAB figure handles
- MATLAB objects
- C, Java, and .NET objects
- Executable data stored in cell arrays and structures

Work with MATLAB Function Handles

MATLAB function handles can be passed between an application and the MATLAB Runtime instance from which it originated. However, a MATLAB function handle cannot be passed into a MATLAB Runtime instance other than the one in which it originated. For example, suppose you had two MATLAB functions, get_plot_handle and plot_xy, and plot xy used the function handle created by get plot handle.

If you compiled them into two packages, the call to plot_xy would throw an exception.

```
import com.mathworks.toolbox.javabuilder.*;
import get plot handle.*;
import plot xv.*;
class plottter
   public static void main(String[] args)
     MWArray h = null;
      try
      {
        plotter_handle = new get_plot_handle.Class1();
        plot = new plot xy.Class1();
        h = plotter_handle.get_plot_handle(1,'--rs',2.0,'k','g',10);
        double[] x = \{1,2,3,4,5,6,7,8,9\};
        double[] y = \{2,6,12,20,30,42,56,72,90\};
        plot.plot_xy(x, y, h);
      }
      catch (Exception e)
         System.out.println("Exception: " + e.toString());
      }
      finally
         MWArray.disposeArray(h);
         plot.dispose();
         plotter handle.dispose();
      }
   }
}
The correct way to handle the situation is to compile both functions into a single package.
import com.mathworks.toolbox.javabuilder.*;
import plot functions.*;
class plotter
   public static void main(String[] args)
   {
```

```
MWArray h = null;
      try
      {
        plot_funcs = new Class1();
        h = plot funcs.get plot handle(1, '--rs', 2.0, 'k', 'g', 10);
        double[] x = \{1,2,3,4,5,6,7,8,9\};
        double[] y = \{2,6,12,20,30,42,56,72,90\};
        plot_funcs.plot_xy(x, y, h);
      }
      catch (Exception e)
         System.out.println("Exception: " + e.toString());
      finally
         MWArray.disposeArray(h);
         plot funcs.dispose();
      }
   }
}
```

Note You could also handle this situation by using a singleton MATLAB Runtime.

Work with Objects

MATLAB Compiler SDK enables you to return the following types of objects from the MATLAB Runtime to your application code:

- MATLAB
- C++
- .NET
- Java

However, you cannot pass an object created in one MATLAB Runtime instance into a different MATLAB Runtime instance. This conflict can happen when a function that returns an object and a function that manipulates that object are compiled into different packages.

For example, you develop two functions. The first creates a bank account for a customer based on some set of conditions. The second transfers funds between two accounts.

```
% Saved as account.m
classdef account < handle</pre>
    properties
        name
    end
    properties (SetAccess = protected)
        balance = 0
        number
    end
    methods
        function obj = account(name)
            obj.name = name;
            obj.number = round(rand * 1000);
        end
        function deposit(obj, deposit)
            new bal = obj.balance + deposit;
            obj.balance = new bal;
        end
        function withdraw(obj, withdrawl)
            new bal = obj.balance - withdrawl;
            obj.balance = new bal;
        end
    end
end
% Saved as open_acct .m
function acct = open_acct(name, open_bal )
    acct = account(name);
    if open bal > 0
        acct.deposit(open bal);
    end
end
```

```
% Saved as transfer.m
function transfer(source, dest, amount)
    if (source.balance > amount)
        dest.deposit(amount);
        source.withdraw(amount);
    end
end
```

If you compiled <code>open_acct.m</code> and <code>transfer.m</code> into separate packages, you could not transfer funds using accounts created with <code>open_acct</code>. The call to <code>transfer</code> throws an exception. One way of resolving this is to compile both functions into a single package. You could also refactor the application such that you are not passing MATLAB objects to the functions.

Note You could also handle this situation by using a singleton MATLAB Runtime.

See Also

More About

"Share MATLAB Runtime Instances" on page 9-14

Error Handling

```
"Error Overview" on page 2-35

"Handling Checked Exceptions" on page 2-35

"Handling Unchecked Exceptions" on page 2-38

"Alternatives to Using of System.exit" on page 2-40
```

Error Overview

Errors that occur during execution of a MATLAB function or during data conversion are signaled by a standard Java exception. This includes MATLAB run-time errors as well as errors in your MATLAB code.

Handling Checked Exceptions

Checked exceptions must be declared as thrown by a method using the throws clause. MATLAB Compiler SDK Java packages support the com.mathworks.toolbox.javabuilder exception.MWException. This exception class inherits from java.lang.Exception and is thrown by every MATLAB Compiler SDK generated Java method to signal that an error has occurred during the call. All normal MATLAB run-time errors, as well as user-created errors (e.g., a calling error in your MATLAB code) are manifested as MWExceptions.

The Java interface to each MATLAB function declares itself as throwing an MWException using the throws clause. For example, the myprimes MATLAB function shown previously has the following interface:

Any method that calls myprimes must do one of two things:

- Catch and handle the MWException.
- Allow the calling program to catch it.

The following two sections provide examples of each.

Handling an Exception in the Called Function

The getprimes example shown here uses the first of these methods. This method handles the exception itself, and does not need to include a throws clause at the start.

```
public double[] getprimes(int n)
{
    myclass cls = null;
    Object[] y = null;

    try
    {
        cls = new myclass();
        y = cls.myprimes(1, new Double((double)n));
        return (double[])((MWArray)y[0]).getData();
    }

    /* Catches the exception thrown by myprimes */
    catch (MWException e)
    {
        System.out.println("Exception: " + e.toString());
        return new double[0];
    }

    finally
```

```
{
    MWArray.disposeArray(y);
    if (cls != null)
        cls.dispose();
    }
}
```

Note that in this case, it is the programmer's responsibility to return something reasonable from the method in case of an error.

The finally clause in the example contains code that executes after all other processing in the try block is executed. This code executes whether or not an exception occurs or a control flow statement like return or break is executed. It is common practice to include any cleanup code that must execute before leaving the function in a finally block. The documentation examples use finally blocks in all the code samples to free native resources that were allocated in the method.

For more information on freeing resources, see "Manage MATLAB Resources" on page 2-41.

Handling an Exception in the Calling Function

In this next example, the method that calls myprimes declares that it throws an MWException:

```
public double[] getprimes(int n) throws MWException
{
    myclass cls = null;
    Object[] y = null;

    try
    {
        cls = new myclass();
        y = cls.myprimes(1, new Double((double)n));
        return (double[])((MWArray)y[0]).getData();
    }

    finally
    {
        MWArray.disposeArray(y);
        if (cls != null)
            cls.dispose();
    }
}
```

Handling Unchecked Exceptions

Several types of unchecked exceptions can also occur during the course of execution. Unchecked exceptions are Java exceptions that do not need to be explicitly declared with a throws clause. The MWArray API classes all throw unchecked exceptions.

All unchecked exceptions thrown by MWArray and its subclasses are subclasses of java.lang.RuntimeException. The following exceptions can be thrown by MWArray:

- java.lang.RuntimeException
- java.lang.ArrayStoreException
- java.lang.NullPointerException
- java.lang.IndexOutOfBoundsException
- java.lang.NegativeArraySizeException

This list represents the most likely exceptions. Others might be added in the future.

Catching General Exceptions

You can easily rewrite the getprimes example to catch any exception that can occur during the method call and data conversion. Just change the catch clause to catch a general java.lang.Exception.

```
public double[] getprimes(int n)
{
    myclass cls = null;
    Object[] y = null;

    try
    {
        cls = new myclass();
        y = cls.myprimes(1, new Double((double)n));
        return (double[])((MWArray)y[0]).getData();
    }

    /* Catches the exception thrown by anyone */
    catch (Exception e)
    {
        System.out.println("Exception: " + e.toString());
        return new double[0];
    }
}
```

```
finally
{
    MWArray.disposeArray(y);
    if (cls != null)
        cls.dispose();
    }
}
```

Catching Multiple Exception Types

This second, and more general, variant of this example differentiates between an exception generated in a compiled method call and all other exception types by introducing two catch clauses as follows:

```
public double[] getprimes(int n)
  myclass cls = null;
  Object[] y = null;
  try
     cls = new myclass();
     y = cls.myprimes(1, new Double((double)n));
      return (double[])((MWArray)y[0]).getData();
  }
  /* Catches the exception thrown by myprimes */
  catch (MWException e)
      System.out.println("Exception in MATLAB call: " +
         e.toString());
      return new double[0];
  }
  /* Catches all other exceptions */
  catch (Exception e)
      System.out.println("Exception: " + e.toString());
      return new double[0];
  }
  finally
     MWArray.disposeArray(y);
      if (cls != null)
```

```
cls.dispose();
}
```

The order of the catch clauses here is important. Because MWException is a subclass of Exception, the catch clause for MWException must occur before the catch clause for Exception. If the order is reversed, the MWException catch clause will never execute.

Alternatives to Using of System.exit

Any Java application that uses a class generated using MATLAB Compiler SDK should avoid any direct or indirect calls to System.exit.

Any direct or indirect call to System.exit will result in the JVM shutting down in an abnormal fashion. This may result in system deadlocks.

Using System.exit also causes the java process to exit unpredictably.

Java programs using Swing components are most likely to invoke System.exit. Here are a few ways to avoid it:

- Use public interface WindowConstants.DISPOSE_ON_CLOSE method as an alternative to WindowConstants.EXIT_ON_CLOSE as input to the JFrame class setDefaultCloseOperation method.
- If you want to provide an Exit button in your GUI that terminates your application, instead of calling System.exit in the ActionListener for the button, call the dispose method on JFrame.

Manage MATLAB Resources

In this section...

"Why MATLAB Resources Need to be Managed" on page 2-41

"Creating MATLAB Objects" on page 2-41

"Disposing of MATLAB Objects" on page 2-42

Why MATLAB Resources Need to be Managed

MATLAB Compiler SDK uses a Java Native Interface (JNI) wrapper connecting your Java application to the C++ MATLAB Runtime. As a result, most of the resources consumed by the MATLAB Compiler SDK portions of your Java application are created by the MATLAB Runtime. Resource created by the MATLAB Runtime are not visible to the JVM. The JVM's garbage collector cannot effectively manage resources that it cannot see.

All of the MATLAB Compiler SDK Java classes have hooks that free the MATLAB resources when the JVM garbage collects the wrapper objects. However, the JVM's garbage collection is unreliable because the JVM only sees the small wrapper object. The garbage collector can decide that it is not worth wasting CPU cycles to actually delete the wrapper object. Until the Java wrapper object is deleted, the resources allocated in the MATLAB Runtime are also not deleted. This behavior can result in conditions that look like memory leaks and rapidly consume resources.

To avoid this situation:

- · Never create anonymous MATLAB objects.
- Always dispose of MATLAB objects using their dispose() method.

Creating MATLAB Objects

All of the MATLAB objects supported by MATLAB Compiler SDK have standard Java constructors as described in the com.mathworks.toolbox.javabuilderJavadoc.

When creating MATLAB objects, always assign them names. To create a 5x5 cell array:

MWCellArray myCA = new MWCellArray(5, 5);

The Java object myCA is a wrapper that points to a 5x5 mxCellArray object in the MATLAB Runtime. myCA can be added to other MATLAB arrays or manipulated in your

Java application. When you are finished with myCA, you can clean up the 5x5 mxCellArray using the object's dispose() method.

The semantics of the API allows you create anonymous MATLAB objects and store them in named MATLAB objects, but you should **never** do this in practice. You have **no way** to manage the MATLAB resources created by the anonymous MATLAB object.

The following code creates a MATLAB array, data, and populates it with an anonymous MATLAB object:

```
MWStructArray data = new MWStructArray(1, KMAX, FIELDS);
data.set(FIELDS[0], k + 1, new MWNumericArray(k * 1.13));
```

Two MATLAB objects are created. Both objects have a Java wrapper and a MATLAB array object in the MATLAB Runtime. When you dispose of data, all of the resources for it are cleaned up. However, the anonymous object created by new MWNumericArray(k * 1.13) is just marked for deletion by the JVM. However, because the Java wrapper consumes a tiny amount of space, the garbage collector is likely to leave it around. Because the JVM never cleans up the wrapper object, the MATLAB Runtime never cleans up the resources it has allocated.

The MATLAB object's set() methods accept native Java types:

```
MWStructArray data = new MWStructArray(1, KMAX, FIELDS);
data.set(FIELDS[0], k + 1, k * 1.13);
```

In this instance, only one MATLAB object is created. When its dispose() method is called all of the resources are cleaned up.

Disposing of MATLAB Objects

There are two ways of cleaning up MATLAB objects:

- the object's dispose() method
- $\bullet \quad \text{the static MWArray.disposeArray() method} \\$

Both methods release all of the resources associated with the MATLAB object. The Java wrapper object is deleted. If there are no other references to the MATLAB Runtime mxArray object, it is also deleted.

The following code disposes of a MATLAB object using its dispose() method.

```
MWCellArray myCA = new MWCellArray(5, 5);
...
myCA.dispose();
The following code disposes of a MATLAB object using the MWArray.disposeArray()
method.
MWCellArray myCA = new MWCellArray(5, 5);
...
MWArray.disposeArray(myCA);
```

MATLAB Runtime User Data Interface

This feature provides a lightweight interface for accessing MATLAB Runtime data. It allows data to be shared between a MATLAB Runtime instance, the MATLAB code running on that MATLAB Runtime, and the wrapper code that created the MATLAB Runtime. Through calls to the MATLAB Runtime User Data interface API, you access MATLAB Runtime data through creation of a per-instance associative array of mxArrays, consisting of a mapping from string keys to mxArray values. Reasons for doing this include, but are not limited to:

- You need to supply run-time information to a client running an application created
 with the Parallel Computing Toolbox™. Profile information may be supplied on a perexecution basis. For example, two instances of the same application may run
 simultaneously with different profiles.
- You want to initialize the MATLAB Runtime with constant values that can be accessed by all your MATLAB applications
- You want to set up a global workspace a global variable or variables that MATLAB and your client can access
- You want to store the state of any variable or group of variables

MATLAB Compiler SDK software supports per-run-time instance state access through an object-oriented API. Access to a per-run-time instance state is optional, rather than on by default. You can access this state by adding setmcruserdata.m and getmcruserdata.m to your deployment project or by specifying them on the command line. Alternatively, you use a helper function to call these methods as demonstrated in "Supply Run-Time Profile Information for Parallel Computing Toolbox Applications" on page 2-45.

For more information, see "Using the MATLAB Runtime User Data Interface"

Supply Run-Time Profile Information for Parallel Computing Toolbox Applications

Following is a complete example of how you can use the MATLAB Runtime User Data Interface as a mechanism to specify a profile for Parallel Computing Toolbox applications.

Step 1: Write Your Parallel Computing Toolbox Code

1 Compile sample pct.m in MATLAB.

This example code uses the cluster defined in the default profile.

The output assumes that the default profile is local.

```
function speedup = sample pct (n)
warning off all;
tic
if(ischar(n))
    n=str2double(n):
end
for ii = 1:n
   (cov(sin(magic(n)+rand(n,n))));
end
time1 =toc:
parpool;
tic
parfor ii = 1:n
   (cov(sin(magic(n)+rand(n,n))));
end
time2 =toc;
disp(['Normal loop times: ' num2str(time1) ...
     ,parallel loop time: ' num2str(time2) ]);
disp(['parallel speedup: ' num2str(1/(time2/time1)) ...
      times faster than normal'l):
delete(gcp);
disp('done');
speedup = (time1/time2);
```

2 Run the code as follows after changing the default profile to local, if needed.

```
a = sample_pct(200)
```

3 Verify that you get the following results:

```
Starting parallel pool (parpool) using the 'local' profile ... connected to 4 worker Normal loop times: 0.7587, parallel loop time: 2.9988 parallel speedup: 0.253 times faster than normal Parallel pool using the 'local' profile is shutting down. done

a =
```

Step 2: Set the Parallel Computing Toolbox Profile

In order to compile MATLAB code to a Java package and utilize the Parallel Computing Toolbox, the mcruserdata must be set directly from MATLAB. There is no Java API available to access the MCRUserdata as there is for C and C++ applications built with MATLAB Compiler SDK.

To set the mcruserdata from MATLAB, create an init function in your Java class. This is a separate MATLAB function that uses setmcruserdata to set the Parallel Computing Toolbox profile once. You then call your other functions to utilize the Parallel Computing Toolbox functions.

Create the following init function:

0.2530

Tip If you need to change your profile in the application, use the parallel.importProfile and parallel.defaultClusterProfile methods. See the Parallel Computing Toolbox documentation for more information.

Step 3: Compile Your Function with the Library Compiler App or the Command Line Compiler

You can compile your function from the command line by entering the following:

```
mcc -S -W 'java:parallelComponent,PctClass' init_sample_pct.m
```

For an example on how to create a Java package using the **Library Compiler** app, see "Generate a Java Package and Build a Java Application".

Use the following information for your project:

Project Name parallelComponent

Class Name PctClass

File to Compile pct_sample.m and init_pct_sample.m

When the compilation finishes, a new folder with the same name as the project is created. This folder contains the following subfolders:

- for redistribution
- for redistribution files only
- for_testing

Note If you are using the GPU feature of Parallel Computing Toolbox, you need to manually add the PTX and CU files.

If you are using the Library Compiler app, click **Add files/directories** on the **Build** tab.

If you are using the \mbox{mcc} command, use the -a option.

Step 4: Write the Java Driver Application

Write the following Java driver application to use the generated package, as follows, using a Java-compatible IDE such as $Eclipse^{TM}$:

```
import com.mathworks.toolbox.javabuilder.*;
import parallelComponent.*;

public class JavaParallelClass
{
    public static void main(String[] args)
    {
        MWArray A = null;
        PctClass C = null;
        Object[] B = null;
```

The output is as follows:

```
(UIGETFILE brings up the window to select the PROFILE file)
Starting parallel pool (parpool) using the 'local' profile ... connected to 4 workers.
Normal loop times: 0.7587, parallel loop time: 2.9988
parallel speedup: 0.253 times faster than normal
Parallel pool using the 'local' profile is shutting down.
done
The Speed Up was:2.1198
```

Compiling and Running the Application Without Using an IDE

If you are not using an IDE, compile the application using command-line Java, as follows:

Note Enter these commands on a single line, using the semi-colon as a delimiter.

Run the application from the command-line, as follows:

See Also

More About

• "MATLAB Runtime User Data Interface" on page 2-44

Dynamically Specify Options to the MATLAB Runtime

In this section...

"What Options Can You Specify?" on page 2-50

"Setting and Retrieving MATLAB Runtime Option Values Using MWApplication" on page 2-50

What Options Can You Specify?

You can pass MATLAB Runtime options -nojvm, -nodisplay, and -logfile to MATLAB Compiler SDK from the client application using two classes in javabuilder.jar:

- MWApplication
- MWMCROption

Setting and Retrieving MATLAB Runtime Option Values Using MWApplication

The MWApplication class provides several static methods to set MATLAB Runtime option values and also to retrieve them. The following table lists static methods supported by this class.

MWApplication Static Methods	Purpose
<pre>MWApplication.initialize(MWMCROption options);</pre>	Passes MATLAB Runtime run-time options (see "Specifying Run-Time Options Using MWMCROption" on page 2-51)
<pre>MWApplication.isMCRInitialized();</pre>	Returns true if the MATLAB Runtime run-time is initialized; otherwise returns false
<pre>MWApplication.isMCRJVMEnabled();</pre>	Returns true if the MATLAB Runtime run-time is launched with JVM; otherwise returns false

MWApplication Static Methods	Purpose
MWApplication.isMCRNoDisplaySet();	Returns true if MWMCROption.NODISPLAY is used in MWApplication.initialize
	Note false is always returned on Windows systems since the - nodisplay option is not supported on Windows systems.
MWApplication.getMCRLogfileName();	Retrieves the name of the log file

Specifying Run-Time Options Using MWMCROption

MWApplication.initialize takes zero or more MWMCROptions.

Calling MWApplication.initialize() without any inputs launches the MATLAB Runtime with the following default values.

You must call MWApplication.initialize() before performing any other processing.

These options are all write-once, read-only properties.

MATLAB Runtime Run-Time Option	Default Values
-nojvm	false
-logfile	null
-nodisplay	false

Note If there are no MATLAB Runtime options being passed, you do not need to use MWApplication.initialize since initializing a generated class initializes the MATLAB Runtime with default options.

Use the following static members of MWMCROption to represent the MATLAB Runtime options you want to modify.

MWMCROption Static Members	Purpose
MWMCROption.NOJVM	Launches the MATLAB Runtime without a JVM. When this option is used, the JVM launched by the client application is unaffected. The value of this option determines whether or not the MATLAB Runtime should attach itself to the JVM launched by the client application.
MWMCROption.NODISPLAY	Launches the MATLAB Runtime without display functionality.
<pre>MWMCROption.logFile("l ogfile.dat")</pre>	Allows you to specify a log file name (must be passed with a log file name).

Passing and Retrieving MATLAB Runtime Option Values from a Java Application

Following is an example of how MATLAB Runtime option values are passed and retrieved from a client-side Java application:

```
MWApplication.initialize(MWMCROption.NOJVM,
    MWMCROption.logFile("logfile.dat"),MWMCROption.NODISPLAY);
System.out.println(MWApplication.getMCRLogfileName());
System.out.println(MWApplication.isMCRInitialized());
System.out.println(MWApplication.isMCRJVMEnabled());
System.out.println(MWApplication.isMCRNoDisplaySet()); //UNIX
myclass cls = new myclass();
cls.hello();
```

Data Conversion Between Java and MATLAB

In this section... "Overview" on page 2-53 "Call MWArray Methods" on page 2-53 "Create Buffered Images from a MATLAB Array" on page 2-54

Overview

The call signature for a method that encapsulates a MATLAB function uses one of the MATLAB data conversion classes to pass arguments and return output. When you call any such method, all input arguments not derived from one of the MWArray classes are converted by the compiler to the correct MWArray type before being passed to the MATLAB method.

For example, consider the following Java statement:

```
result = theFourier.plotfft(3, data, new Double(interval));
```

The third argument is of type java.lang.Double, which converts to a MATLAB 1-by-1 double array.

See "Rules for Data Conversion Between Java and MATLAB" on page 9-4 for a complete list of rules to convert between Java and MATLAB Compiler SDK data types.

Call MWArray Methods

The conversion rules apply not only when calling your own methods, but also when calling constructors and factory methods belonging to the MWArray classes. For example, the following code calls the constructor for the MWNumericArray class with a Java double input. The MATLAB Compiler SDK product converts the Java double input to an instance of MWNumericArray having a ClassID property of MWClassID.DOUBLE. This is the equivalent of a MATLAB 1-by-1 double array.

```
double Adata = 24;
MWNumericArray A = new MWNumericArray(Adata);
System.out.println("Array A is of type " + A.classID());
```

When you run this example, the results are as follows:

Array A is of type double

Specifying the Type

To specify the MATLAB to Java type conversion, you supply a specific data type in the constructor. The MATLAB Compiler SDK product converts to the specified type rather than following the default conversion rules.

The following code specifies that A should be constructed as a MATLAB 1-by-1 16-bit integer array:

```
double Adata = 24;
MWNumericArray A = new MWNumericArray(Adata, MWClassID.INT16);
```

Create Buffered Images from a MATLAB Array

Use the renderArrayData method to:

- Create a buffered image from data in a given MATLAB array.
- Verify the array is of three dimensions (height, width, and color component).
- Verify the color component order is red, green, and blue.

Search on renderArrayData in the Javadoc for information on input parameters, return values, exceptions thrown, and examples. The Javadoc is located at matlabroot/help/javabuilder/MWArrayAPI.

Set Java Properties

In this section...

"How to Set Java System Properties" on page 2-55

"Ensure a Consistent GUI Appearance" on page 2-55

How to Set Java System Properties

Set Java system properties in one of two ways:

- In the Java statement. Use the syntax: java -Dpropertyname=value, where propertyname is the name of the Java system property you want to set and value is the value to which you want the property set.
- *In the Java code*. Insert the following statement in your Java code near the top of the main function, before you initialize any Java classes:

```
System.setProperty(key,value)
```

key is the name of the Java system property you want to set, and *value* is the value to which you want the property set.

Ensure a Consistent GUI Appearance

After developing your initial GUI using the MATLAB Compiler SDK product, subsequent GUIs that you develop may inherit properties of the MATLAB GUI, rather than properties of your initial design. To preserve your original look and feel, set the mathworks.DisableSetLookAndFeel Java system property to true.

Setting DisableSetLookAndFeel

The following are examples of how to set mathworks.DisableSetLookAndFeel using the techniques in "How to Set Java System Properties" on page 2-55:

• In the java statement:

```
java -classpath X:/mypath/tomy/javabuilder.jar -
Dmathworks.DisableSetLookAndFeel=true
```

In the Java code:

Execution of Applications that Create Figures

The following example illustrates using waitForFigures from a Java application. The example uses a Java class created by the MATLAB Compiler SDK product; the object encapsulates MATLAB code that draws a simple plot.

- 1 Create a work folder for your source code. In this example, the folder is D:\work \plotdemo.
- **2** In this folder, create the following MATLAB file:

```
drawplot.m
function drawplot()
    plot(1:10);
```

3 Use the compiler to create a Java package with the following properties:

```
Package name examples
Class name Plotter
```

4 Create a Java program in a file named runplot. java with the following code:

```
import com.mathworks.toolbox.javabuilder.*;
import examples.Plotter;

public class runplot
{
    public static void main(String[] args)
    {
        try
        {
            plotter p = new Plotter();
            try
            {
                 p.drawplot();
                 p.waitForFigures();
        }
        finally
        {
                p.dispose();
        }
        catch (MWException e)
        {
                e.printStackTrace();
        }
}
```

} } }

5 Compile the application with the javac command.

When you run the application, the program displays a plot from 1 to 10 in a MATLAB figure window. The application ends when you dismiss the figure.

Note To see what happens without the call to waitForFigures, comment out the call, rebuild the application, and run it. In this case, the figure is drawn and is immediately destroyed as the application exits.

Ensuring Multi-Platform Portability

Compiled MATLAB code containing only MATLAB files are platform independent, as are .jar files. These files can be used out of the box on any platform providing that the platform has either MATLAB or the MATLAB Runtime installed.

However, if your compiled MATLAB code contains MEX-files, which are platform dependent, do the following:

- **1** Compile your MEX-file once on each platform where you want to run your application.
 - For example, if you are running on a Windows machine, and you want to also run on the Linux 64-bit platform, compile my_mex.c twice (once on a PC to get my_mex.mexw64 and then again on a Linux 64-bit machine to get my_mex.mexa64).
- Compile the package on one platform using the mcc command, using the -a flag to include the MEX-file compiled on the other platform(s). In the example above, run mcc on Windows and include the -a flag to include my_mex.mexa64. In this example, the mcc command would be:

```
mcc -W 'java:mycomp,myclass' my matlab file.m -a my mex.mexa64
```

Note In this example, it is not necessary to explicitly include $my_mex.mexw64$ (providing you are running on Windows). This example assumes that $my_mex.mexw64$ and $my_mex.mexa64$ reside in the same folder.

For example, if you are running on a Windows machine and you want to ensure portability of the generated package that invokes the yprimes.c file (from matlabroot\extern \examples\mex) on the Linux 64-bit platform, execute the following mcc command:

```
mcc -W 'java:mycomp,myclass' callyprime.m -a yprime.mexa64
where callyprime.m can be a simple MATLAB function as follows:
```

function callyprime
disp(yprime(1,1:4));

Ensure the yprime.mexa64 file is in the same folder as your Windows MEX-file.

Tip If you are unsure if your JAR file contains MEX-files, do the following:

- 1 Run mcc with the -v option to list the names of the MEX-files.
- **2** Obtain appropriate versions of these files from the version of MATLAB installed on your target operating system.
- 3 Include these versions in the archive by running mcc with the -a option.

Caution Some toolbox functionality will not be deployable when compiled into a Java package and run on a platform other than the one compiled on. This is because some toolbox code includes data that may be platform specific. If this is the case, you can only deploy the application to like platforms. For example, the Image Processing Toolbox function IMHIST will fail if deployed cross-platform with an undefined function error.

JAR files produced by MATLAB Compiler SDK are tested and qualified to run on platforms supported by MATLAB. See the Platform Roadmap for MATLAB for more information.

Deployable Archive Embedding and Extraction

In this section...

"Overview" on page 2-61

"Use MWComponentOptions Class to Indicate Extraction Options" on page 2-61

"Use Environment Variables to Indicate Extraction Options" on page 2-63

"For More Information" on page 2-64

Overview

Deployable archive data is extracted from the JAR file with no separate deployable archive or *packageNamemcr* folder needed on the target machine. This behavior is helpful when storage space on a file system is limited.

If you don't want deployable archive data extracted by default, use either the MWComponentOptions class, or use environment variables, to specify how deployable archive data extraction and utilization is handled.

Use MWComponentOptions Class to Indicate Extraction Options

Selecting Options

Choose from the following CtfSource or ExtractLocation instantiation options to customize how to manage deployable archive content with MWComponentOptions:

- CtfSource This option specifies where the deployable archive may be found for an
 extracted component. It defines a binary data stream comprised of the bits of the
 deployable archive. The following values are objects of some type extending
 MWCtfSource:
 - MWCtfSource.NONE Indicates that no deployable archive is to be extracted.
 This implies that the extracted deployable archive data is already accessible somewhere on your file system. This is a public, static, final instance of MWCtfSource.
 - MWCtfFileSource Indicates that the deployable archive data resides within a
 particular file location that you specify. This class takes a java.io.File object in
 its constructor.

- MWCtfDirectorySource Indicates a folder to be scanned when instantiating
 the component: if a file with a .ctf suffix is found in the folder you supply, the
 deployable archive bits are loaded from that file. This class takes a java.io.File
 object in its constructor.
- MWCtfStreamSource Allows deployable archive bits to be read and extracted directly from a specified input stream. This class takes a java.io.InputStream object in its constructor.
- ExtractLocation This option specifies where the extracted deployable archive content is to be located. Since the MATLAB Runtime requires all deployable archive content be located somewhere on your file system, use the desired ExtractLocation option, along with the component type information, to define a unique location. A value for this option is an instance of the class MWCtfExtractLocation. An instance of this class can be created by passing a java.io.File or java.lang.String into the constructor to specify the file system location to be used or one of these predefined, static final instances may be used:
 - MWCtfExtractLocation.EXTRACT_TO_CACHE Use to indicate that the deployable archive content is to be placed in the MATLAB Runtime component cache. This is the default setting for R2007a and forward.
 - MWCtfExtractLocation.EXTRACT_TO_COMPONENT_DIR Use when you want
 to locate the JAR or .class files from which the component has been loaded. If the
 location is found (e.g., it is on the file system), then the deployable archive data is
 extracted into the same folder. This option most closely matches the behavior of
 R2007a and previous releases.

Note Deployable archives are extracted by default to <code>temp\user_name \mcrCachen.nn</code>.

Setting Options

Use the following methods to get or set the location where the deployable archive may be found for an extracted component:

- getCtfSource()
- setCtfSource()

Use the following methods to get or set the location where the extracted deployable archive content is to be located:

- getExtractLocation()
- setExtractLocation()

Enabling MATLAB Runtime Component Cache, Utilizing Deployable Archive Content Already on Your System

If you want to enable the MATLAB Runtime Component Cache for a generated Java class utilizing deployable archive content already resident in your file system, instantiate MWComponentOptions using the following statements:

```
MWComponentOptions options = new MWComponentOptions();

// set options for the class by calling setter methods
// on 'options'
options.setCtfSource(MWCtfSource.NONE);
  options.setExtractLocation(
    new MWCtfExtractLocation("C:\\readonlydir\\MyModel_mcr"));

// instantiate the class using the desired options
MyModel m = new MyModel(options);
```

Use Environment Variables to Indicate Extraction Options

Use the following environment variables to change these settings.

Environment Variable	Purpose	Notes
MCR_CACHE_ROOT	When set to the location of where you want the deployable archive to be extracted, this variable overrides the default per-user component cache location. This is true for embedded .ctf files only.	Does not apply

Environment Variable	Purpose	Notes
MCR_CACHE_SIZE		The initial limit for this variable is 32M (megabytes). This may, however, be changed after you have set the variable the first time. Edit the file .max_size, which resides in the file designated by running the mcrcachedir command, with the desired cache size limit.

Overriding Default Behavior

To extract the deployable archive, compile using the -C option when calling mcc.

You can also implement this override by entering -C in the **Settings** editor of the Library Compiler app.

You might want to use this option to troubleshoot problems with the deployable archive, for example, as the log and diagnostic messages are much more visible.

For More Information

For more information about the deployable archive, see "Deployable Archive" (MATLAB Compiler).

Explore the Javadoc

The Javadoc can be browsed from <code>matlabroot/help/javabuilder/MWArrayAPI</code> in your product installation and by entering the name of the class or method you want to learn more about in the search field on the <code>Index</code> page.

Javadoc contains, among other information:

- · Signatures that diagram method and class usage
- · Parameters passed in, return values expected, and exceptions that can be thrown
- · Examples demonstrating typical usage of the class or method

Distribute Integrated Java Applications

- "Package Java Applications" on page 3-2
- "About the MATLAB Runtime" on page 3-3
- "Install and Configure the MATLAB Runtime" on page 3-5

Package Java Applications

- **1** Gather and package the following files for installation on end user computers:
 - MATLAB Runtime installer

See "Install and Configure the MATLAB Runtime" on page 3-5.

- MATLAB generated Java package
- JAR files for the application
- **2** Include directions for installing the MATLAB Runtime.

See "Install and Configure the MATLAB Runtime" on page 3-5.

3 Include directions for adding the required JAR files to the Java CLASSPATH.

At a minimum, the CLASSPATH must include:

- mcrroot/toolbox/javabuilder/jar/javabuilder.jar
- MATLAB generated Java package
- JAR files for the application

About the MATLAB Runtime

In this section...

"How is the MATLAB Runtime Different from MATLAB?" on page 3-3

"Performance Considerations and the MATLAB Runtime" on page 3-4

The MATLAB Runtime is a standalone set of shared libraries, MATLAB code, and other files that enables the execution of MATLAB files on computers without an installed version of MATLAB. Applications that use artifacts built with MATLAB Compiler SDK require access to an appropriate version of the MATLAB Runtime to run.

End-users of compiled artifacts without access to MATLAB must install the MATLAB Runtime on their computers or know the location of a network-installed MATLAB Runtime. The installers generated by the compiler apps may include the MATLAB Runtime installer. If you compiled your artifact using mcc, you should direct your endusers to download the MATLAB Runtime installer from the website https://www.mathworks.com/products/compiler/mcr.

See "Install and Configure the MATLAB Runtime" on page 3-5 for more information.

How is the MATLAB Runtime Different from MATLAB?

The MATLAB Runtime differs from MATLAB in several important ways:

- In the MATLAB Runtime, MATLAB files are encrypted and immutable.
- MATLAB has a desktop graphical interface. The MATLAB Runtime has all the MATLAB functionality without the graphical interface.
- The MATLAB Runtime is version-specific. You must run your applications with the
 version of the MATLAB Runtime associated with the version of MATLAB Compiler SDK
 with which it was created. For example, if you compiled an application using version
 6.3 (R2016b) of MATLAB Compiler, users who do not have MATLAB installed must
 have version 9.1 of the MATLAB Runtime installed. Use mcrversion to return the
 version number of the MATLAB Runtime.
- The MATLAB paths in a MATLAB Runtime instance are fixed and cannot be changed. To change them, you must first customize them within MATLAB.

Performance Considerations and the MATLAB Runtime

MATLAB Compiler SDK was designed to work with a large range of applications that use the MATLAB programming language. Because of this, run-time libraries are large.

Since the MATLAB Runtime technology provides full support for the MATLAB language, including the Java programming language, starting a compiled application takes approximately the same amount of time as starting MATLAB. The amount of resources consumed by the MATLAB Runtime is necessary in order to retain the power and functionality of a full version of MATLAB.

Calls into the MATLAB Runtime are serialized so calls into the MATLAB Runtime are threadsafe. This can impact performance.

Install and Configure the MATLAB Runtime

In this section...

"Download the MATLAB Runtime Installer from the Web" on page 3-5

"Install the MATLAB Runtime Interactively" on page 3-5

"Install the MATLAB Runtime Non-Interactively" on page 3-7

"Install the MATLAB Runtime without Administrator Rights" on page 3-9

"Multiple MATLAB Runtime Versions on Single Machine" on page 3-9

"MATLAB and MATLAB Runtime on Same Machine" on page 3-10

"Uninstall MATLAB Runtime" on page 3-11

Download the MATLAB Runtime Installer from the Web

Download the MATLAB® Runtime from the website at https://www.mathworks.com/products/compiler/matlab-runtime.html.

Install the MATLAB Runtime Interactively

To install the MATLAB Runtime:

1 Unzip/Extract the archive containing the MATLAB Runtime installer.

Platform	Steps
Windows	Unzip the MATLAB Runtime installer. To unzip the installer:
	Right click the zip file MATLAB_Runtime_R2019b_win64.zip
	Select Extract All, and then follow the instructions.
Linux	Unzip the MATLAB Runtime installer at the terminal using the unzip command.
	For example, if you are unzipping the R2019b MATLAB Runtime installer, at the Terminal, type:
	unzip MATLAB_Runtime_R2019b_glnxa64.zip

Platform	Steps
macOS	Unzip the MATLAB Runtime installer at the terminal using the unzip command.
	For example, if you are unzipping the R2019b MATLAB Runtime installer, at the Terminal, type:
	unzip MATLAB_Runtime_R2019b_maci64.zip

Note The release part of the installer filename (_R2019b_) will change from one release to the next.

Start the MATLAB Runtime installer.

Platform	Steps
Windows	Double-click the file setup.exe from the extracted files to start the installer.
Linux	At the Terminal, type: sudo ./install
	Note On Debian® based Linux distributions, you will need to type: gksudo ./install
macOS	At the Terminal, type: ./install
	Note You may need to enter an administrator username and password after you run ./install.

- When the MATLAB Runtime installer starts, it displays a dialog box. Read the information and then click **Next** to proceed with the installation.
- **4** Specify the folder in which you want to install the MATLAB Runtime in the **Folder Selection** dialog box.

Note On Windows systems, you can have multiple versions of the MATLAB Runtime on your computer but only one installation for any particular version. If you already have an existing installation, the MATLAB Runtime installer does not display the **Folder Selection** dialog box because you can only overwrite the existing installation in the same folder.

- 5 Confirm your choices and click **Next**.
 - The MATLAB Runtime installer starts copying files into the installation folder.
- 6 On Linux and macOS platforms, after copying files to your disk, the MATLAB Runtime installer displays the **Product Configuration Notes** dialog box. This dialog box contains information necessary for setting your path environment variables. Copy the path information from this dialog box and then click **Next**.
- **7** Click **Finish** to exit the installer.

Install the MATLAB Runtime Non-Interactively

To install the MATLAB Runtime without having to interact with the installer dialog boxes, use one of the MATLAB Runtime installer's non-interactive modes:

- silent—the installer runs as a background task and does not display any dialog boxes
- automated—the installer displays the dialog boxes but does not wait for user interaction

When run in silent or automated mode, the MATLAB Runtime installer uses default values for installation options. You can override these defaults by using MATLAB Runtime installer command-line options or an installer control file.

Note When running in silent or automated mode, the installer overwrites the default installation location.

Running the Installer in Silent Mode

To install the MATLAB Runtime in silent mode:

1 Extract the contents of the MATLAB Runtime installer file to a temporary folder, called **\$temp** in this documentation.

Note On Windows systems, **manually** extract the contents of the installer file.

2 Run the MATLAB Runtime installer, specifying the -mode option and -agreeToLicense yes on the command line.

Note On most platforms, the installer is located at the root of the folder into which the archive was extracted. On Windows 64, the installer is located in the archives bin folder.

Platform	Command
Windows	setup -mode silent - agreeToLicense yes
Linux	./install -mode silent - agreeToLicense yes
macOS	./install -mode silent - agreeToLicense yes

Note If you do not include the -agreeToLicense yes the installer will not install the MATLAB Runtime.

- **3** View a log of the installation.
 - On Windows systems, the MATLAB Runtime installer creates a log file, named mathworks_username.log, where username is your Windows log-in name, in the location defined by your TEMP environment variable.
- 4 On Linux and macOS systems, specify the path variable. The MATLAB Runtime installer displays the log information for Linux and macOS systems at the command prompt, unless you redirect it to a file.

Customizing a Non-Interactive Installation

When run in one of the non-interactive modes, the installer will use the default values unless told to do otherwise. Like the MATLAB installer, the MATLAB Runtime installer accepts a number of command line options that modify the default installation properties.

Option	Description
	Specifies where the MATLAB Runtime will be installed.

Option	Description
-outputFile	Specifies where the installation log file is written.
-automatedModeTimeout	Specifies how long, in milliseconds, that the dialog boxes are displayed when run in automatic mode.
-inputFile	Specifies an installer control file with the values for all of the above options.

Note The MATLAB Runtime installer archive includes an example installer control file called installer_input.txt. This file contains all of the options available for a full MATLAB installation. Only the options listed in this section are valid for the MATLAB Runtime installer.

Install the MATLAB Runtime without Administrator Rights

To install the MATLAB Runtime as a user without administrator rights on Windows:

- **1** Use the MATLAB Runtime installer to install it on a Windows machine where you have administrator rights.
- 2 Copy the folder where the MATLAB Runtime was installed to the machine without administrator rights. You can compress the folder into zip file and distribute to multiple users.
- **3** On the machine without administrator rights, add the <code>mcr_root\runtime\arch</code> directory onto the user's path environment variable.

Note You don't need administrator rights for adding directories to a user's path environment variable.

Multiple MATLAB Runtime Versions on Single Machine

MCRInstaller supports the installation of multiple versions of the MATLAB Runtime on a target machine. This allows applications compiled with different versions of the MATLAB Runtime to execute side by side on the same machine.

If you do not want multiple MATLAB Runtime versions on the target machine, you can remove the unwanted ones. On Windows, run **Add or Remove Programs** from the

Control Panel to remove any of the previous versions. On Linux, you manually delete the unwanted MATLAB Runtime. You can remove unwanted versions before or after installation of a more recent version of the MATLAB Runtime, as versions can be installed or removed in any order.

MATLAB and MATLAB Runtime on Same Machine

You do not need to install MATLAB Runtime on your machine if your machine has MATLAB installed. The version of MATLAB should be the same as the version of MATLAB that was used to create the compiled MATLAB code. Also, to act as the MATLAB Runtime replacement, the MATLAB installation must include MATLAB Compiler.

You can, however, install the MATLAB Runtime for debugging purposes.

Modifying the Path

If you install MATLAB Runtime on a machine that already has MATLAB on it, you must adjust the library path according to your needs.

Windows

To run deployed MATLAB code against MATLAB Runtime install, mcr_root\ver \runtime\win64 must appear on your system path before matlabroot\runtime \win64.

If $mcr_root\ver\$ runtime\arch appears first on the compiled application path, the application uses the files in the MATLAB Runtime install area.

If *matlabroot*\runtime\arch appears first on the compiled application path, the application uses the files in the MATLAB installation area.

Linux

To run deployed MATLAB code against MATLAB Runtime on Linux, the folder <mcr_root>/runtime/<arch> must appear on your LD_LIBRARY_PATH before matlabroot/runtime/<arch>.

macOS

To run deployed MATLAB code on macOS, the <mcr_root>/runtime folder must appear on your DYLD LIBRARY PATH before matlabroot/runtime/<arch>.

To run MATLAB on macOS or Intel® Mac, matlabroot/runtime/<arch> must appear on your DYLD_LIBRARY_PATH before the <mcr_root>/bin folder.

Uninstall MATLAB Runtime

The method you use to uninstall MATLAB Runtime from your computer varies depending on the type of computer.

Windows

1 Start the uninstaller.

From the Windows Start menu, search for the **Add or Remove Programs** control panel, and double-click MATLAB Runtime in the list.

You can also start the MATLAB Runtime uninstaller from the mcr_root\uninstall \bin\arch folder, where mcr_root is your MATLAB Runtime installation folder and arch is an architecture-specific folder, such as win64.

- **2** Select the MATLAB Runtime from the list of products in the Uninstall Products dialog box.
- 3 Click Next.
- 4 Click Finish.

Linux

- **1** Exit the application.
- **2** Enter this command at the Linux prompt:

```
rm -rf mcr root
```

where mcr_root represents the name of your top-level MATLAB installation folder.

macOS

- **1** Exit the application.
- 2 Navigate to your MATLAB Runtime installation folder. For example, the installation folder might be named MATLAB_Compiler_Runtime.app in your Applications folder.
- 3 Drag your MATLAB Runtime installation folder to the trash, and then select **Empty Trash** from the Finder menu.

Distribute to End Users

- "MATLAB Runtime Path Settings for Development and Testing" on page 4-2
- "MATLAB Runtime Path Settings for Run-Time Deployment" on page 4-4

MATLAB Runtime Path Settings for Development and Testing

In this section...

"Path for Java Development on All Platforms" on page 4-2

"Path Modifications Required for Accessibility" on page 4-2

"Windows Settings for Development and Testing" on page 4-2

"Linux Settings for Development and Testing" on page 4-2

"OS X Settings for Development and Testing" on page 4-3

Path for Java Development on All Platforms

There are additional requirements when programming in the Java programming language. For more information see "Configure Your Java Environment" on page 1-3.

Path Modifications Required for Accessibility

In order to use some screen-readers or assistive technologies, such as JAWS®, you must add the following DLLs to your Windows path:

matlabroot\sys\java\jre\arch\jre\bin\JavaAccessBridge.dll
matlabroot\sys\java\jre\arch\jre\bin\WindowsAccessBridge.dll

You may not be able to use such technologies without doing so.

Windows Settings for Development and Testing

When programming with compiled MATLAB code, add the following folder to your system PATH environment variable:

matlabroot\runtime\win32|win64

Linux Settings for Development and Testing

Add the following platform-specific folders to your dynamic library path.

Note For readability, the following commands appear on separate lines, but you must enter each setenv command on one line.

setenv LD_LIBRARY_PATH
 matlabroot/runtime/glnxa64:
 matlabroot/bin/glnxa64:
 matlabroot/sys/os/glnxa64:
 matlabroot/sys/opengl/lib/glnxa64

OS X Settings for Development and Testing

Add the following platform-specific folders to your dynamic library path.

Note For readability, the following commands appear on separate lines, but you must enter each seteny command on one line.

setenv DYLD_LIBRARY_PATH
 matlabroot/runtime/maci64:
 matlabroot/bin/maci64:
 matlabroot/sys/os/maci64:

MATLAB Runtime Path Settings for Run-Time Deployment

In this section...

"General Path Guidelines" on page 4-4

"Path for Java Applications on All Platforms" on page 4-4

"Windows Path for Run-Time Deployment" on page 4-4

"Linux Paths for Run-Time Deployment" on page 4-5

"OS X Paths for Run-Time Deployment" on page 4-5

General Path Guidelines

Regardless of platform, be aware of the following guidelines with regards to placing specific folders on the path:

- Always avoid including arch on the path. Failure to do so may inhibit ability to run multiple MATLAB Runtime instances.
- Ideally, set the environment in a separate shell script to avoid run-time errors caused by path-related issues.

Path for Java Applications on All Platforms

When your users run applications that contain compiled MATLAB code, you must instruct them to set the path so that the system can find the MATLAB Runtime.

Note When you deploy a Java application to end users, they must set the class path on the target machine.

The system needs to find .jar files containing the MATLAB libraries. To tell the system how to locate the .jar files it needs, specify a classpath either in the javac command or in your system environment variables.

Windows Path for Run-Time Deployment

The following folder should be added to the system path:

mcr_root\version\runtime\win64

mcr_root refers to the complete path where the MATLAB Runtime library archive files are installed on the machine where the application is to be run.

 mcr_root is version specific; you must determine the path after you install the MATLAB Runtime.

Note If you are running the MATLAB Runtime installer on a shared folder, be aware that other users of the share may need to alter their system configuration.

Linux Paths for Run-Time Deployment

Use these setenv commands to set your MATLAB Runtime paths.

```
setenv LD_LIBRARY_PATH
   mcr_root/version/runtime/glnxa64:
   mcr_root/version/bin/glnxa64:
   mcr_root/version/sys/os/glnxa64:
   mcr_root/version/sys/opengl/lib/glnxa64
```

OS X Paths for Run-Time Deployment

Use these setenv commands to set your MATLAB Runtime paths.

```
setenv DYLD_LIBRARY_PATH
  mcr_root/version/runtime/maci64:
  mcr_root/version/bin/maci64:
  mcr_root/version/sys/os/maci64
```

Sample Java Applications

- "Display a MATLAB Plot in a Java Application" on page 5-2
- "Create a Java Application with Two MATLAB Functions" on page 5-7
- "Matrix Math" on page 5-12
- "Phone Book" on page 5-21
- "Pass Java Objects to MATLAB" on page 5-27
- "Display a MATLAB Plot on the Web using a Java Servlet" on page 5-37

Note Remember to double-quote all parts of the java command paths that contain spaces. To test directly against the MATLAB Runtime when executing java, substitute mcrroot for matlabroot, where mcrroot is the location where the MATLAB Runtime is installed on your system.

Display a MATLAB Plot in a Java Application

In this section...

"Purpose" on page 5-2

"Procedure" on page 5-2

Purpose

The purpose of the example is to show you how to do the following:

- Use the MATLAB Compiler SDK product to convert a MATLAB function (drawplot.m) to a method of a Java class (plotter) and wrap the class in a Java package (plotdemo).
- Access the MATLAB function in a Java application (createplot.java) by instantiating the plotter class and using the MWArray class library to handle data conversion.

Note For complete reference information about the MWArray class hierarchy, see the com.mathworks.toolbox.javabuilder package.

• Build and run the createplot.java application.

The drawplot.m function displays a plot of input parameters x and y.

Procedure

- **1** If you have not already done so, copy the files for this example as follows:
 - a Copy the following folder that ships with MATLAB to your work folder:
 - matlabroot\toolbox\javabuilder\Examples\PlotExample
 - b At the MATLAB command prompt, cd to the new PlotExample subfolder in your work folder.
- 2 If you have not already done so, set the environment variables that are required on a development machine. See "Configure Your Java Environment" on page 1-3.
- **3** Write the drawplot.m function as you would any MATLAB function.

The following code defines the drawplot.m function:

```
function drawplot(x,y)
plot(x,y);
```

This code is already in your work folder in PlotExample\PlotDemoComp\drawplot.m.

4 While in MATLAB, issue the following command to open the Library Compiler app:

libraryCompiler

5 You create a Java package by using the Library Compiler app to build a Java class that wraps around your MATLAB code. For an example, see "Generate a Java Package and Build a Java Application".

Use the following information for your project:

Project Name plotdemo
Class Name plotter
File to compile drawplot.m

6 Write source code for an application that accesses the MATLAB function.

The sample application for this example is in *matlabroot*\toolbox\javabuilder \Examples\PlotExample\PlotDemoJavaApp\createplot.java.

The program graphs a simple parabola from the equation $y = x^2$.

The program listing is shown here.

createplot.java

```
/* Necessary package imports */
import com.mathworks.toolbox.javabuilder.*;
import plotdemo.*;
* createplot class demonstrates plotting x-y data into
* a MATLAB figure window by graphing a simple parabola.
class createplot
  public static void main(String[] args)
                               /* Array of x values */
     MWNumericArray x = null;
     MWNumericArray y = null;
                                /* Array of y values */
     plotter thePlot = null;
                                /* Plotter class instance */
     int n = 20:
                                 /* Number of points to plot */
      try
         /* Allocate arrays for x and y values */
         int[] dims = \{1, n\};
```

```
x = MWNumericArray.newInstance(dims,
            MWClassID.DOUBLE, MWComplexity.REAL);
         y = MWNumericArray.newInstance(dims,
            MWClassID.DOUBLE, MWComplexity.REAL);
         /* Set values so that y = x^2 */
         for (int i = 1; i \le n; i++)
            x.set(i, i);
            y.set(i, i*i);
         /* Create new plotter object */
         thePlot = new plotter();
         /* Plot data */
         thePlot.drawplot(x, y);
         thePlot.waitForFigures();
      catch (Exception e)
         System.out.println("Exception: " + e.toString());
      }
      finally
         /* Free native resources */
         MWArray.disposeArray(x);
         MWArray.disposeArray(y);
         if (thePlot != null)
            thePlot.dispose();
     }
  }
}
```

The program does the following:

- Creates two arrays of double values, using MWNumericArray to represent the data needed to plot the equation.
- Instantiates the plotter class as thePlot object, as shown:

```
thePlot = new plotter();
```

 Calls the drawplot method to plot the equation using the MATLAB plot function, as shown:

```
thePlot.drawplot(x,y);
```

- Uses a try-catch block to catch and handle any exceptions.
- 7 Compile the createplot application using javac. When entering this command, ensure there are no spaces between path names in the matlabroot argument. For example, there should be no space between javabuilder.jar; and .\distrib \plotdemo.jar in the following example. cd to your work folder. Ensure createplot.java is in your work folder

• On Windows, execute this command:

```
javac -classpath
  .; matlabroot\toolbox\javabuilder\jar\javabuilder.jar;
  .\distrib\plotdemo.jar createplot.java
```

• On UNIX, execute this command:

```
javac -classpath
  .:matlabroot/toolbox/javabuilder/jar/javabuilder.jar:
  ./distrib/plotdemo.jar createplot.java
```

Run the application. 8

To run the createplot.class file, do one of the following:

On Windows, type:

```
java -classpath
  .; matlabroot\toolbox\javabuilder\jar\javabuilder.jar;
  .\distrib\plotdemo.jar
  createplot
```

On UNIX, type:


```
iava -classpath
  .: matlabroot/toolbox/javabuilder/jar/javabuilder.jar:
  ./distrib/plotdemo.jar
  createplot
```

Note You should be using the same major version of Java that ships with MATLAB. To find out what version of Java MATLAB is running, enter the following MATLAB command:

```
version - java
```

Note If you are running on the Mac 64-bit platform, you must add the -d64 flag in the Java command. See "Limitations of the MATLAB Compiler SDK Java Target" on page 9-3 for more specific information.

The createplot program should display the output.



Create a Java Application with Two MATLAB Functions

In this section...

"Purpose" on page 5-7

"Procedure" on page 5-7

Purpose

The purpose of the example is to show you the following:

- How to use the MATLAB Compiler SDK product to create a package containing a class that has a private method that is automatically encapsulated.
- How to access the MATLAB functions in a Java application, including use of the MWArray class hierarchy to represent data

Note For complete reference information about the MWArray class hierarchy, see the com.mathworks.toolbox.javabuilder package.

• How to build and run the application

The spectralanalysis package analyzes a signal and graphs the result. The class, fourier, performs a fast Fourier transform (FFT) on an input data array. A method of this class, computefft, returns the results of that FFT as two output arrays—an array of frequency points and the power spectral density. The second method, plotfft, graphs the returned data. These two methods, computefft and plotfft, encapsulate MATLAB functions.

The MATLAB code for these two methods is in computefft.m and plotfft.m, which is found in matlabroot\toolbox\javabuilder\Examples\SpectraExample \SpectraDemoComp.

Procedure

- **1** If you have not already done so, copy the files for this example as follows:
 - a Copy the following folder that ships with MATLAB to your work folder: matlabroot\toolbox\javabuilder\Examples\SpectraExample

- **b** At the MATLAB command prompt, cd to the new SpectraExample subfolder in your work folder.
- **2** If you have not already done so, set the environment variables that are required on a development machine. See "Configure Your Java Environment" on page 1-3.
- **3** Write the MATLAB code that you want to access.

This example uses computefft.m and plotfft.m which are already in your work folder in SpectraExample\SpectraDemoComp.

- **4** Open the Library Compiler app.
- 5 Create the Java package by using the Library Compiler app to build a Java class that wraps your MATLAB code. For an example on how to create a Java package using the **Library Compiler** app, see "Generate a Java Package and Build a Java Application".

Use the following information for your project:

Project Name spectralanalysis
Class Name fourier
File to compile plotfft.m

Note In this example, the application that uses the fourier class does not need to call computefft directly. The computefft method is required only by the plotfft method. Thus, when creating the package, you do not need to add the computefft function, although doing so does no harm.

6 Write source code for an application that accesses the MATLAB functions.

The sample application for this example is in SpectraExample \SpectraDemoJavaApp\powerspect.java.

The program listing is shown here.

powerspect.java

```
/* Number of samples */
      int nSamples = 1001;
      MWNumericArray data = null; /* Stores input data */
      Object[] result = null; /* Stores result */
      fourier theFourier = null; /* Fourier class instance */
      try
      {
          * Construct input data as sin(2*PI*15*t) +
          * sin(2*PI*40*t) plus a random signal.
               Duration = 10
               Sampling interval = 0.01
         int[] dims = {1, nSamples};
         data = MWNumericArray.newInstance(dims, MWClassID.DOUBLE,
                                              MWComplexity.REAL);
         for (int i = 1; i <= nSamples; i++)
         {
            double t = (i-1)*interval;
            double x = Math.sin(2.0*Math.PI*15.0*t) +
               Math.sin(2.0*Math.PI*40.0*t) +
               Math.random();
            data.set(i, x);
         }
         /* Create new fourier object */
         theFourier = new fourier();
         theFourier.waitForFigures();
         /* Compute power spectral density and plot result */
         result = theFourier.plotfft(3, data,
            new Double(interval));
      }
      catch (Exception e)
         System.out.println("Exception: " + e.toString());
      }
      finally
         /* Free native resources */
         MWArray.disposeArray(data);
         MWArray.disposeArray(result);
         if (theFourier != null)
            theFourier.dispose();
  }
}
```

The program does the following:

- Constructs an input array with values representing a random signal with two sinusoids at 15 and 40 Hz embedded inside of it
- Creates an MWNumericArray array that contains the data, as shown:

```
data = MWNumericArray.newInstance(dims, MWClassID.DOUBLE, MWComplexity.REAL);
```

Instantiates a fourier object

- Calls the plotfft method, which calls computeftt and plots the data
- Uses a try-catch block to handle exceptions
- Frees native resources using MWArray methods
- 7 Compile the powerspect.java application using javac. When entering this command, ensure there are no spaces between path names in the matlabroot argument. For example, there should be no space between javabuilder.jar; and .\distrib\spectralanalysis.jar in the following example.

Open a Command Prompt window and cd to the *matlabroot*\spectralanalysis folder. cd to your work folder. Ensure powerspect.java is in your work folder

On Windows, execute the following command:

```
javac -classpath
.;matlabroot\toolbox\javabuilder\jar\javabuilder.jar;
.\distrib\spectralanalvsis.jar powerspect.java
```

• On UNIX, execute the following command:

```
javac -classpath
.:matlabroot/toolbox/javabuilder/jar/javabuilder.jar:
./distrib/spectralanalysis.jar powerspect.java
```

Note For *matlabroot* substitute the root MATLAB folder on your system. Type matlabroot to see this folder name.

- **8** Run the application.
 - On Windows, execute the powerspect class file:

```
java -classpath
.;matlabroot\toolbox\javabuilder\jar\javabuilder.jar
.\distrib\spectralanalysis.jar
powerspect
```

• On UNIX, execute the powerspect class file:


```
java -classpath
.:matlabroot/toolbox/javabuilder/jar/javabuilder.jar:
./distrib/spectralanalysis.jar
powerspect
```

Note You should be using the same major version of Java that ships with MATLAB. To find out what version of Java MATLAB is running, enter the following MATLAB command:

version -java

Note If you are running on the Mac 64-bit platform, you must add the -d64 flag in the Java command. See "Limitations of the MATLAB Compiler SDK Java Target" on page 9-3 for more specific information.

The powerspect program should display the output:



Matrix Math

In this section...

"Purpose" on page 5-12

"MATLAB Functions to Be Encapsulated" on page 5-13

"Understanding the getfactor Program" on page 5-13

"Procedure" on page 5-14

Purpose

The purpose of the example is to show you the following:

- How to assign more than one MATLAB function to a generated class.
- How to manually handle native memory management.
- How to access the MATLAB functions in a Java application (getfactor.java) by instantiating Factor and using the MWArray class library to handle data conversion.

Note For complete reference information about the MWArray class hierarchy, see the com.mathworks.toolbox.javabuilder package.

• How to build and run the MatrixMathDemoApp application

This example builds a Java package to perform matrix math. The example creates a program that performs Cholesky, LU, and QR factorizations on a simple tridiagonal matrix (finite difference matrix) with the following form:

You supply the size of the matrix on the command line, and the program constructs the matrix and performs the three factorizations. The original matrix and the results are printed to standard output. You may optionally perform the calculations using a sparse matrix by specifying the string "sparse" as the second parameter on the command line.

MATLAB Functions to Be Encapsulated

The following code defines the MATLAB functions used in the example:

```
    cholesky.m
        function [L] = cholesky(A)
        L = chol(A);
    ludecomp.m
        function [L,U] = ludecomp(A)
        [L,U] = lu(A);
    qrdecomp.m
        function [Q,R] = qrdecomp(A)
        [Q,R] = qr(A);
```

Understanding the getfactor Program

The <code>getfactor</code> program takes one or two arguments from standard input. The first argument is converted to the integer order of the test matrix. If the string <code>sparse</code> is passed as the second argument, a sparse matrix is created to contain the test array. The Cholesky, LU, and QR factorizations are then computed and the results are displayed to standard output.

The main method has three parts:

- The first part sets up the input matrix, creates a new factor object, and calls the cholesky, ludecomp, and qrdecomp methods. This part is executed inside of a try block. This is done so that if an exception occurs during execution, the corresponding catch block will be executed.
- The second part is the catch block. The code prints a message to standard output to let the user know about the error that has occurred.
- The third part is a finally block to manually clean up native resources before exiting.

Procedure

Step-by-Step Procedure

- **1** If you have not already done so, copy the files for this example as follows:
 - **a** Copy the following folder that ships with MATLAB to your work folder:
 - matlabroot\toolbox\javabuilder\Examples\MatrixMathExample
 - **b** At the MATLAB command prompt, cd to the new MatrixMathExample subfolder in your work folder.
- **2** If you have not already done so, set the environment variables that are required on a development machine. See "Configure Your Java Environment" on page 1-3.
- **3** Write the MATLAB functions as you would any MATLAB function.

The code for cholesky.m, ludecomp.m, and qrdecomp.m functions is already in your work folder in MatrixMathExample\MatrixMathDemoComp\.

- **4** Select Library Compiler app.
- Create the Java package using the Library Compiler app to build a Java class that wraps around your MATLAB code. For an example, see "Generate a Java Package and Build a Java Application".

Use the following information for your project:

Project Name factormatrix

Class Name factor

Files to compile cholesky.m, ludecomp.m, and

grdecomp.m

6 Write source code for an application that accesses the MATLAB functions.

The sample application for this example is in MatrixMathExample \MatrixMathDemoJavaApp\getfactor.java.

The program listing is shown here.

getfactor.java

```
/* Necessary package imports */
import com.mathworks.toolbox.javabuilder.*;
import factormatrix.*;
/*
    * getfactor class computes cholesky, LU, and QR
    * factorizations of a finite difference matrix
```

```
* of order N. The value of N is passed on the
 * command line. If a second command line arg
 * is passed with the value of "sparse", then
 * a sparse matrix is used.
*/
class getfactor
   public static void main(String[] args)
      MWNumericArray a = null; /* Stores matrix to factor */
                                /* Stores the result */
      Object[] result = null;
      factor theFactor = null;
                                /* Stores factor class instance */
      try
         /* If no input, exit */
         if (args.length == 0)
            System.out.println("Error: must input a positive integer");
            return;
         }
         /* Convert input value */
         int n = Integer.valueOf(args[0]).intValue();
         if (n \le 0)
         {
            System.out.println("Error: must input a positive integer");
            return;
         }
          * Allocate matrix. If second input is "sparse"
          * allocate a sparse array
         int[] dims = {n, n};
         if (args.length > 1 && args[1].equals("sparse"))
            a = MWNumericArray.newSparse(dims[0], dims[1],n+2*(n-1),
                                  MWClassID.DOUBLE, MWComplexity.REAL);
         else
            a = MWNumericArray.newInstance(dims,MWClassID.DOUBLE, MWComplexity.REAL);
         /* Set matrix values */
         int[] index = {1, 1};
         for (index[0] = 1; index[0] \le dims[0]; index[0]++)
            for (index[1] = 1; index[1] \le dims[1]; index[1]++)
            {
               if (index[1] == index[0])
               a.set(index, 2.0);
else if (index[1] == index[0]+1 || index[1] == index[0]-1)
                  a.set(index, -1.0);
         }
         /* Create new factor object */
         theFactor = new factor();
         /* Print original matrix */
         System.out.println("Original matrix:");
```

```
System.out.println(a);
        /* Compute cholesky factorization and print results. */
        result = theFactor.cholesky(1, a);
        System.out.println("Cholesky factorization:");
        System.out.println(result[0]);
        MWArray.disposeArray(result);
        /* Compute LU factorization and print results. */
        result = theFactor.ludecomp(2, a);
        System.out.println("LU factorization:");
        System.out.println("L matrix:");
        System.out.println(result[0]);
        System.out.println("U matrix:");
        System.out.println(result[1]);
        MWArray.disposeArray(result);
        /* Compute QR factorization and print results. */
        result = theFactor.qrdecomp(2, a);
        System.out.println("QR factorization:");
        System.out.println("Q matrix:");
        System.out.println(result[0]);
        System.out.println("R matrix:");
        System.out.println(result[1]);
     }
     catch (Exception e)
        System.out.println("Exception: " + e.toString());
     finally
        /* Free native resources */
        MWArray.disposeArray(a);
        MWArray.disposeArray(result);
        if (theFactor != null)
           theFactor.dispose();
     }
  }
}
           The statement:
           theFactor = new factor();
           creates an instance of the class factor.
           The following statements call the methods that encapsulate the MATLAB functions:
           result = theFactor.cholesky(1, a);
           result = theFactor.ludecomp(2, a);
           result = theFactor.grdecomp(2, a);
            . . .
```

- 7 Copy getfactor. java into the factormatrix folder.
- 8 Compile the getfactor application using javac. When entering this command, ensure there are no spaces between path names in the matlabroot argument. For example, there should be no space between javabuilder.jar; and .\distrib \factormatrix.jar in the following example.

cd to the factormatrix folder in your work folder.

• On Windows, execute the following command:

```
javac -classpath
.;matlabroot\toolbox\javabuilder\jar\javabuilder.jar;
.\distrib\factormatrix.jar getfactor.java
```

• On UNIX, execute the following command:

```
javac -classpath
.:matlabroot/toolbox/javabuilder/jar/javabuilder.jar:
./distrib/factormatrix.jar getfactor.java
```

9 Run the application.

Run getfactor using a nonsparse matrix

• On Windows, execute the getfactor class file as follows:

```
java -classpath
.;matlabroot\toolbox\javabuilder\jar\javabuilder.jar;
.\distrib\factormatrix.jar
getfactor 4
```

• On UNIX, execute the getfactor class file as follows:

```
java -classpath
.:matlabroot/toolbox/javabuilder/jar/javabuilder.jar:
./distrib/factormatrix.jar
getfactor 4
```

Note You should be using the same major version of Java that ships with MATLAB. To find out what version of Java MATLAB is running, enter the following MATLAB command:

```
version -java
```

Note If you are running on the Mac 64-bit platform, you must add the -d64 flag in the Java command. See "Limitations of the MATLAB Compiler SDK Java Target" on page 9-3 for more specific information.

Output for the Matrix Math Example

```
Original matrix:
     2
           - 1
                   0
                         0
    - 1
            2
                  -1
                         0
     0
           -1
                  2
                         - 1
     0
            0
                  - 1
                         2
Cholesky factorization:
              -0.7071
    1.4142
                                           0
          0
               1.2247
                         -0.8165
                                           0
          0
                     0
                          1.1547
                                     -0.8660
          0
                     0
                                      1.1180
                                0
LU factorization:
L matrix:
    1.0000
                     0
                                0
                                           0
   -0.5000
               1.0000
                                0
                                           0
          0
              -0.6667
                           1.0000
                                           0
          0
                     0
                         -0.7500
                                      1.0000
U matrix:
    2.0000
              -1.0000
                                           0
          0
               1.5000
                         -1.0000
          0
                     0
                          1.3333
                                     -1.0000
          0
                     0
                                0
                                      1.2500
QR factorization:
Q matrix:
   -0.8944
              -0.3586
                         -0.1952
                                      0.1826
                         -0.3904
    0.4472
              -0.7171
                                      0.3651
          0
               0.5976
                         -0.5855
                                      0.5477
          0
                     0
                          0.6831
                                      0.7303
R matrix:
                         -0.4472
   -2.2361
               1.7889
                                           0
```

To run the same program for a sparse matrix, use the same command and add the string sparse to the command line:

java (... same arguments) getfactor 4 sparse

Output for a Sparse Matrix

```
Original matrix:
   (1,1)
                 2
   (2,1)
                - 1
   (1,2)
                -1
                2
   (2,2)
   (3,2)
                - 1
   (2,3)
                -1
   (3,3)
                2
   (4,3)
                -1
   (3,4)
                - 1
   (4,4)
                 2
```

Cholesky factorization:

(1,1)	1.4142
(1,2)	-0.7071
(2,2)	1.2247
(2,3)	-0.8165
(3,3)	1.1547
(3,4)	-0.8660
(4,4)	1.1180

LU factorization:

L matrix:

(1,1)	1.0000
(2,1)	-0.5000
(2,2)	1.0000
(3,2)	-0.6667
(3,3)	1.0000
(4,3)	-0.7500
(4,4)	1.0000

U matrix: (1,1) (1,2) (2,2) (2,3) (3,3) (3,4) (4,4)	2.0000 -1.0000 1.5000 -1.0000 1.3333 -1.0000 1.2500
QR factoriza Q matrix: (1,1) (2,1) (1,2)	0.8944 -0.4472 0.3586
(1,2) (2,2) (3,2) (1,3) (2,3) (3,3) (4,3)	0.7171 -0.5976 0.1952 0.3904 0.5855 -0.6831
(1,4) (2,4) (3,4) (4,4)	0.1826 0.3651 0.5477 0.7303
R matrix: (1,1) (1,2) (2,2) (1,3) (2,3) (3,3) (2,4) (3,4) (4,4)	2.2361 -1.7889 1.6733 0.4472 -1.9124 1.4639 0.5976 -1.9518 0.9129

Phone Book

Purpose

An example of how to process an MWStructArray as output from a generated class might be:

```
Object[] tmp = myComponent.myFunction(1, myArray);
MWStructArray myStruct = (MWStructArray) tmp[0];
```

The makephone function takes a structure array as an input, modifies it, and supplies the modified array as an output.

Note For complete reference information about the MWArray class hierarchy, see the com.mathworks.toolbox.javabuilder package.

Procedure

- **1** If you have not already done so, copy the files for this example as follows:
 - **a** Copy the following folder that ships with MATLAB to your work folder:
 - matlabroot\toolbox\javabuilder\Examples\PhoneExample
 - **b** At the MATLAB command prompt, cd to the new PhoneExample subfolder in your work folder.
- **2** If you have not already done so, set the environment variables that are required on a development machine. See "Configure Your Java Environment" on page 1-3.
- **3** Write the makephone function as you would any MATLAB function.

The following code defines the makephone function:

```
function book = makephone(friends)
book = friends;
for i = 1:numel(friends)
    numberStr = num2str(book(i).phone);
    book(i).external = ['(508) 555-' numberStr];
end
```

This code is already in your work folder in makephone.m.

4 Select Library Compiler app.

5 Create a Java Package using the Library Compiler app to build a Java class that wraps around your MATLAB code. For an example, see "Generate a Java Package and Build a Java Application".

Use the following information for your project:

Project Name phonebookdemo
Class Name phonebook
File to compile makephone.m

6 Write source code for an application that accesses the MATLAB functions.

The sample application for this example is in *matlabroot*\toolbox\javabuilder \Examples\PhoneExample\PhoneDemoJavaApp\qetphone.java.

The program defines a structure array containing names and phone numbers, modifies it using a MATLAB function, and displays the resulting structure array.

The program listing is shown here.

getphone.java

```
/* Necessary package imports */
import com.mathworks.toolbox.javabuilder.*;
import phonebookdemo.*;
   getphone class demonstrates the use of the MWStructArray class
class getphone
    public static void main(String[] args)
        phonebook thePhonebook = null;
                                               /* Stores magic class instance */
        MWStructArray friends = null; /* Sample input data */
Object[] result = null; /* Stores the result */
        MWStructArray book = null; /* Output data extracted from result */
        try
             /* Create new magic object */
             thePhonebook = new phonebook();
             /* Create an MWStructArray with two fields */
             String[] myFieldNames = {"name", "phone"};
             friends = new MWStructArray(2,2,myFieldNames);
             /* Populate struct with some sample data --- friends and phone numbers */
             friends.set("name",1,new MWCharArray("Jordan Robert"));
friends.set("phone",1,3386);
             friends.set("name",2,new MWCharArray("Mary Smith"));
             friends.set("phone",2,3912);
```

```
friends.set("name",3,new MWCharArray("Stacy Flora"));
        friends.set("phone",3,3238);
friends.set("name",4,new MWCharArray("Harry Alpert"));
        friends.set("phone",4,3077);
        /* Show some of the sample data */
        System.out.println("Friends: ");
        System.out.println(friends.toString());
        /* Pass it to a MATLAB function that determines external phone number */
        result = thePhonebook.makephone(1, friends);
        book = (MWStructArray)result[0];
        System.out.println("Result: ");
        System.out.println(book.toString());
        /* Extract some data from the returned structure */
        System.out.println("Result record 2:");
        System.out.println(book.getField("name",2));
        System.out.println(book.getField("phone",2));
        System.out.println(book.getField("external",2));
        /* Print the entire result structure using the helper function below */
        System.out.println("");
        System.out.println("Entire structure:");
        dispStruct(book);
    catch (Exception e)
    {
        System.out.println("Exception: " + e.toString());
    }
    finally
        /* Free native resources */
        MWArray.disposeArray(result);
        MWArray.disposeArray(friends);
        MWArray.disposeArray(book);
        if (thePhonebook != null)
            thePhonebook.dispose();
    }
}
public static void dispStruct(MWStructArray arr) {
    System.out.println("Number of Elements: " + arr.numberOfElements());
    //int numDims = arr.numberOfDimensions();
    int[] dims = arr.getDimensions();
    System.out.print("Dimensions: " + dims[0]);
    for (int i = 1; i < dims.length; i++)
    {
        System.out.print("-by-" + dims[i]);
    System.out.println("");
    System.out.println("Number of Fields: " + arr.numberOfFields());
    System.out.println("Standard MATLAB view:");
    System.out.println(arr.toString());
    System.out.println("Walking structure:");
    java.lang.String[] fieldNames = arr.fieldNames();
    for (int element = 1; element <= arr.numberOfElements(); element++) {</pre>
        System.out.println("Element " + element);
        for (int field = 0; field < arr.numberOfFields(); field++) {</pre>
            MWArray fieldVal = arr.getField(fieldNames[field], element);
            /* Recursively print substructures, give string display of other classes */
```

The program does the following:

- Creates a structure array, using MWStructArray to represent the example phonebook data.
- Instantiates the plotter class as thePhonebook object, as shown: thePhonebook
 new phonebook();
- Calls the makephone method to create a modified copy of the structure by adding an additional field, as shown: result = thePhonebook.makephone(1, friends);
- Uses a try-catch block to catch and handle any exceptions.
- 7 Compile the getphone application using javac. When entering this command, ensure there are no spaces between path names in the matlabroot argument. For example, there should be no space between javabuilder.jar; and .\distrib \phonebookdemo.jar in the following example. cd to your work folder. Ensure getphone.java is in your work folder
 - On Windows, execute this command:

```
javac -classpath
    .;matlabroot\toolbox\javabuilder\jar\javabuilder.jar;
    .\distrib\phonebookdemo.jar getphone.java
```

• On UNIX, execute this command:

```
javac -classpath
    .:matlabroot/toolbox/javabuilder/jar/javabuilder.jar:
    ./distrib/phonebookdemo.jar getphone.java
```

8 Run the application.

To run the getphone.class file, do one of the following:

• On Windows, type:

Note You should be using the same major version of Java that ships with MATLAB. To find out what version of Java MATLAB is running, enter the following MATLAB command:

```
version -java
```

Note If you are running on the Mac 64-bit platform, you must add the -d64 flag in the Java command. See "Limitations of the MATLAB Compiler SDK Java Target" on page 9-3 for more specific information.

The getphone program should display the output:

```
Friends:

2x2 struct array with fields:
    name
    phone

Result:

2x2 struct array with fields:
    name
    phone
    external

Result record 2:

Mary Smith

3912

(508) 555-3912

Entire structure:
```

```
Number of Elements: 4
Dimensions: 2-by-2
Number of Fields: 3
Standard MATLAB view:
2x2 struct array with fields:
    name
    phone
    external
Walking structure:
Element 1
   name: Jordan Robert
   phone: 3386
   external: (508) 555-3386
Element 2
   name: Mary Smith
   phone: 3912
   external: (508) 555-3912
Element 3
   name: Stacy Flora
   phone: 3238
   external: (508) 555-3238
Element 4
   name: Harry Alpert
   phone: 3077
   external: (508) 555-3077
```

Pass Java Objects to MATLAB

In this section...

"Purpose" on page 5-27

"OptimDemo Package" on page 5-27

"Prerequisites" on page 5-28

"Procedure" on page 5-29

Purpose

The purpose of this example is to show you how to:

- Use the MATLAB Compiler SDK product to create a package that applies MATLAB optimization routines to objective functions implemented as Java objects.
- Access the MATLAB functions in a Java application, including use of the MWJavaObjectRef class to create a reference to a Java object and pass it to the generated Java methods.

Note For complete reference information about the MWArray class hierarchy, see the com.mathworks.toolbox.javabuilderJavadoc package in matlabroot/help/toolbox/javabuilder/MWArrayAPI.

Build and run the application.

OptimDemo Package

- The OptimDemo package finds a local minimum of an objective function and returns the minimal location and value.
- The package uses the MATLAB optimization function fminsearch, and this example optimizes the Rosenbrock banana function used in the MATLAB fminsearch documentation.
- The class, Optimizer, performs an unconstrained nonlinear optimization on an objective function implemented as a Java object.
- A method of this class, doOptim, accepts an initial guess and Java object that implements the objective function, and returns the location and value of a local minimum.

- The second method, displayObj, is a debugging tool that lists the characteristics of a Java object.
- The two methods, doOptim and displayObj, encapsulate MATLAB functions. The MATLAB code for these two methods is in doOptim.m and displayObj.m, which can be found in matlabroot\toolbox\javabuilder\Examples\ObjectRefExample \ObjectRefDemoComp.

Prerequisites

• Start this example by creating a new work folder that is visible to the MATLAB search path. In this example, we will use the following folders:

Windows: c:\matlab\work

Linux: ~/matlab/work

- If you have not already done so, set the environment variables that are required on a
 development machine. For more information, see "Configure Your Java Environment"
 on page 1-3.
- Copy the following files to the work folder:

File(s)	From	То
javabuilder.j ar	<pre>matlabroot\toolbox \javabuilder\jar\win64</pre>	Windows: c:\matlab\work
	() 0 1 0 0 0 1 1 0 0 1	Linux: ~/matlab/work
doOptim.m	matlabroot\toolbox	Windows: c:\matlab\work
displayObj.m	\javabuilder\Examples \ObjectRefExample \ObjectRefDemoComp	Linux: ~/matlab/work
	matlabroot\toolbox	Windows: c:\matlab\work
n.java	\javabuilder\Examples \ObjectRefExample	Linux: ~/matlab/work
PerformOptim. java	\ObjectRefDemoJavaApp	

Your work folder should now have the following five files:

c:\matlab\work
javabuilder.jar
doOptim.m

```
displayObj.m
BananaFunction.java
PerformOptim.java
```

Procedure

- 1 Open MATLAB and cd to the work folder you created in the prerequisite section.
- Write the MATLAB code you want to access from Java. This example uses doOptim.m and displayObj.m, which are already in your work folder.

For reference, the code from doOptim.m is displayed here:

```
function [x,fval] = doOptim(h, x0)
directEval = h.evaluateFunction(x0)
wrapperEval = mWrapper(x0)
[x,fval] = fminsearch(mWrapper,x0)
```

For reference, the code from displayObj.m is displayed here:

```
function className = displayObj(h)
h
className = class(h)
whos('h')
methods(h)
```

- 3 At the MATLAB command prompt, type libraryCompiler to open the Library Compiler app.
- 4 Use the **Library Compiler** app to create a Java package from the MATLAB functions doOptim.m and displayObj.m. Use the following naming conventions for your package:

Save the project in your work folder using OptimDemo

the name:

Library Name: OptimDemo Class Name: Optimizer

Exported Functions (files to compile): doOptim.m and displayObj.m

The Java classes created by the **Library Compiler** app serve as wrapper around the MATLAB code.

The **Library Compiler** app will create a folder by the name **OptimDemo** in the c:\matlab\work directory. The **OptimDemo** folder contains the following sub folders:

```
for_redistribution
for_redistribution_files_only
for_testing
```

The files that you will need for the rest of the example are located in the for testing folder.

For more information on working with the **Library Compiler** app, see "Generate a Java Package and Build a Java Application".

Write source code for a class that implements an object function to optimize. The code for this example is in file BananaFunction.java. The program listing is shown here:

```
public class BananaFunction {
    public BananaFunction() {}
    public double evaluateFunction(double[] x)
    {
        /* Implements the Rosenbrock banana function described in
            * the FMINSEARCH documentation
            */
            double term1 = 100*java.lang.Math.pow((x[1]-Math.pow(x[0],2.0)),2.0);
            double term2 = Math.pow((1-x[0]),2.0);
            return term1 + term2;
      }
}
```

The class implements the Rosenbrock banana function described in the MATLAB fminsearch documentation.

Write source code for an application that accesses the MATLAB functions. The code for this example is in the file PerformOptim.java. The program listing is shown here:

```
/* Necessary package imports */
import com.mathworks.toolbox.javabuilder.*;
import OptimDemo.*;
* Demonstrates the use of the MWJavaObjectRef class
* Takes initial point for optimization as two arguments:
     PerformOptim -1.2 1.0
*/
class PerformOptim
    public static void main(String[] args)
       Optimizer theOptimizer = null;
                                              /* Stores component
                                       instance */
                                         /* Java object reference to
       MWJavaObjectRef origRef = null;
                                     be passed to component */
       MWJavaObjectRef outputRef = null;
                                             /* Output data extracted
                                        from result */
                                    /* Initial point for optimization */
       MWNumericArray x0 = null;
                                    /* Location of minimal value */
       MWNumericArray x = null;
       MWNumericArray fval = null; /* Minimal function value */
       Object[] result = null; /* Stores the result */
       try
            /* If no input, exit */
           if (args.length < 2)
                System.out.println("Error: must input initial x0 1
                                            and x0 2 position");
                return:
            }
            /* Instantiate a new Java object */
            /* This should only be done once per application instance */
            theOptimizer = new Optimizer();
            try {
                /* Initial point --- parse data from text fields */
                double[] x0Data = new double[2];
                x0Data[0] = Double.valueOf(args[0]).doubleValue();
                x0Data[1] = Double.valueOf(args[1]).doubleValue();
                x0 = new MWNumericArray(x0Data, MWClassID.D0UBLE);
                System.out.println("Using x0 =");
```

```
System.out.println(x0);
   /* Create object reference to objective function object */
   BananaFunction objectiveFunction = new BananaFunction();
   origRef = new MWJavaObjectRef(objectiveFunction);
   /* Pass Java object to a MATLAB function that lists its
               methods, etc */
   System.out.println("** Properties of Java object
   result = theOptimizer.displayObj(1, origRef);
   MWArray.disposeArray(result);
   System.out.println("** Finished DISPLAYOBJ *********");
   /* Call the Java component to optimize the function */
   /* using the MATLAB function FMINSEARCH */
   System.out.println("** Unconstrained nonlinear optim**");
   result = theOptimizer.doOptim(2, origRef, x0);
   try {
      System.out.println("** Finished DOOPTIM ***** *******");
      x = (MWNumericArray)result[0];
      fval = (MWNumericArray)result[1];
      /* Display the results of the optimization */
      System.out.println("Location of minimum: ");
      System.out.println(x);
      System.out.println("Function value at minimum: ");
      System.out.println(fval.toString());
   finally
   {
      MWArray.disposeArray(result);
finally
   /* Free native resources */
   MWArray.disposeArray(origRef);
   MWArray.disposeArray(outputRef);
   MWArray.disposeArray(x0);
```

```
}
catch (Exception e)
{
    System.out.println("Exception: " + e.toString());
}

finally
{
    /* Free native resources */
    if (theOptimizer != null)
        theOptimizer.dispose();
}
}
```

The program accomplishes the following:

- Instantiates an object of the BananaFunction class above to be optimized.
- Creates an MWJavaObjectRef that references the BananaFunction object, as shown: origRef = new MWJavaObjectRef(objectiveFunction);.
- Instantiates an Optimizer object.
- Calls the displayObj method to verify that the Java object is being passed correctly.
- Calls the doOptim method, which uses fminsearch to find a local minimum of the objective function.
- Uses a try/catch block to handle exceptions.
- Frees native resources using MWArray methods.
- 7 Compile the PerformOptim.java application and BananaFunction.java helper class using the Java command javac. When entering this command, ensure there are no spaces between path names separated by a semicolon (;).
 - 1 Open a Command Prompt or Terminal window and cd to the work folder.
 - 2 Compile the application according to which operating system you are running on:

Windows

To compile BananaFunction.java, type:

```
javac -classpath .;
c:\matlab\work\javabuilder.jar;
c:\matlab\work\OptimDemo\for_testing\OptimDemo.jar BananaFunction.java
```

```
To compile PerformOptim.java, type:
       javac -classpath .;
       c:\matlab\work\javabuilder.jar;
       c:\matlab\work\OptimDemo\for testing\OptimDemo.jar PerformOptim.java
       Linux
       To compile BananaFunction.java, type:
       javac -classpath .:
       ~/matlab/work/javabuilder.jar:
       ~/matlab/work/OptimDemo/for testing/OptimDemo.jar BananaFunction.java
       To compile PerformOptim.java, type:
       javac -classpath .:
       ~/matlab/work/javabuilder.jar:
       ~/matlab/work/OptimDemo/for testing/OptimDemo.jar PerformOptim.java
8
   Execute the PerformOptim class file as follows:
   On Windows, type:
   java -classpath .;
   c:\matlab\work\javabuilder.jar;
   c:\matlab\work\OptimDemo\for_testing\OptimDemo.jar PerformOptim -1.2 1.0
   On Linux, type:
   java -classpath .:
   ~/matlab/work/javabuilder.jar:
   ~/matlab/work/OptimDemo/for testing/OptimDemo.jar PerformOptim -1.2 1.0
```

Note You should be using the same major version of Java that ships with MATLAB. To find out what version of Java MATLAB is running, enter the following MATLAB command:

version -java

Note If you are running on the Mac 64-bit platform, you must add the -d64 flag in the Java command. See "Limitations of the MATLAB Compiler SDK Java Target" on page 9-3 for more specific information.

When run successfully, the PerformOptim program should display the following output:

```
Using x0 =
-1.2000
         1.0000
*******************
** Properties of Java object
******************
h =
BananaFunction@1766806
className =
BananaFunction
         Size
                       Bytes Class
                                           Attributes
 Name
 h
          1x1
                            BananaFunction
Methods for class BananaFunction:
BananaFunction
               getClass
                              notifyAll
equals
              hashCode
                             toString
evaluateFunction notify
                             wait
** Finished DISPLAYOBJ ****************
******************
** Performing unconstrained nonlinear optimization **
************************************
directEval =
  24.2000
wrapperEval =
  24.2000
x =
           1.0000
   1.0000
fval =
```

8.1777e-10

Optimization successful
** Finished DOOPTIM *******************
Location of minimum:
1.0000 1.0000
Function value at minimum:
8.1777e-10

Display a MATLAB Plot on the Web using a Java Servlet

In this section...

"Overview" on page 5-37

"Prerequisites" on page 5-37

"Locating and Copying the Example Files" on page 5-38

"Build Your Java Package" on page 5-39

"Compiling Your Java Code" on page 5-39

"Generating the Web Archive (WAR) File" on page 5-40

"Running the Web Deployment Example" on page 5-40

"Using the Web Application" on page 5-40

Overview

This example demonstrates how to display a plot created by a Java servlet calling a class created with the MATLAB Compiler SDK product over a Web interface. This example uses MATLAB varargin and varargout for optional input and output to the varargexample.m function. For more information about varargin and varargout, see "Specify Optional Arguments" on page 2-16.

Prerequisites

This section describes what you need to know and do before you create the Web deployment example.

- "Ensure You Have the Required Products" on page 5-37
- "Ensure Your Web Server Is Java Compliant" on page 5-38
- "Install the javabuilder.jar Library" on page 5-38

Ensure You Have the Required Products

The following products must be installed at their recommended release levels.

- MATLAB, MATLAB Compiler, MATLAB Compiler SDK
- Java Development Kit (JDK)

Ensure you have a JDK installed on your system. You can download it from Oracle, Inc.

Note You should be using the same major version of Java that ships with MATLAB. To find out what version of Java MATLAB is running, enter the following MATLAB command:

version -java

Ensure Your Web Server Is Java Compliant

In order to run this example, your Web server must be capable of running accepted Java frameworks like J2EE.

Install the javabuilder.jar Library

Ensure that the javabuilder.jar library (matlabroot/toolbox/javabuilder.jar) has been installed into your Web server's common library folder.

Locating and Copying the Example Files

The example files are located in the *matlabroot*\toolbox\javabuilder\Examples \java_web_vararg_demo folder.

Contents of the Example Files

The example files contain the following three folders:

- mcode Contains all of the MATLAB source code.
- JavaCode Contains the required Java files and libraries.
- compile Contains some helpful MATLAB functions to compile and clean up the example.

Note As an alternative to compiling the example code manually and creating the application WAR (Web Archive) manually, you can run compileVarArgServletDemo.m in the compile folder. If you choose this option and want to change the locations of the output files, edit the values in getVarArgServletDemoSettings.m.

If you choose to run compileVarArgServletDemo.m, consult the readme file in the download for additional information and then skip to "Running the Web Deployment Example" on page 5-40.

Copy the Example Files

Copy the folder <code>java_web_vararg_demo</code> containing example files to a local folder. Failure to do so may lead to errors.

Build Your Java Package

Build your Java package by compiling your code into a deployable .jar file.

- **1** Open the Library Compiler app.
- 2 Create the Java package using the Library Compiler app to build a Java class that wraps around your MATLAB code. For an example on how to create a Java package using the **Library Compiler** app, see "Generate a Java Package and Build a Java Application"

Use the following information for your project:

Project Name vararg_java
Class Name vararg_javaclass

File to compile varargexample.m

Compiling Your Java Code

Use javac to compile the Java source file VarArgServletClass.java from example folder JavaCode\src\VarArg.

<code>javac.exe</code> should be located in the bin folder of your JDK installation.

Ensure your classpath is set to include:

- javabuilder.jar included with MATLAB Compiler SDK
- vararg_java.jar the JAR file you just built
- servlet-api.jar included as part of the servlet container

For more details about using <code>javac</code>, see the Oracle website.

Generating the Web Archive (WAR) File

Web archive or WAR files are a type of Java Archive used to deploy J2EE and JSP servlets. To run this example you will need to use the jar command to generate the final WAR file that runs the application. To do this, follow these steps:

- 1 Copy the JAR file created using the MATLAB Compiler SDK product into the JavaCode\build\WEB-INF\classes\VarArg example folder.
- Copy the compiled Java class to the JavaCode\build\WEB-INF\classes\VarArg example folder.
- From the folder JavaCode, use the jar command to generate the final WAR as follows:

```
jar cf VarArgServlet.war -C build .
```

Caution Don't omit the . parameter above, which denotes the current working folder.

For more information about the jar command, refer to the Oracle Web site.

Running the Web Deployment Example

When you're ready to run the application, do the following:


- 1 Install the VarArgServlet.war file into your Web server's webapps folder.
- Run the application by entering http://localhost:port_number/ VarArgServlet in the address field of your Web browser, where port_number is the port that your Web server is configured to use (usually 8080).

Using the Web Application

To use the application, do the following on the http://localhost/VarArgServlet Web page:



- **1** Enter any amount of numbers to plot in the **Data to Plot** field.
- Select Line Color and Border Color using the Optional Input drop-down lists. Note that these optional inputs are passed as varargin to the compiled MATLAB code.
- 3 Select additional information you want to output, such as mean and standard deviation, by clicking an option in the **Optional Output** area. Note that these optional outputs are set as varargout from the compiled MATLAB code.
- 4 Click **Display Plot**. Example output is shown below using the **Mean** optional output.



Working with MATLAB Figures and Images

- "Roles in Working with Figures and Images" on page 6-2
- "Work with MATLAB Image Data" on page 6-3

Roles in Working with Figures and Images

When you work with figures and images as a MATLAB programmer, you are responsible for:

- Preparing a MATLAB figure for export
- Making changes to the figure (optional)
- Exporting the figure
- Cleaning up the figure window

When you work with figures and images as a front-end Web developer, some of the tasks you are responsible for include:

- · Getting a WebFigure from a deployed component
- Getting raw image data from a deployed component converted into a byte array
- · Getting a buffered image from a component
- Getting a buffered image or a byte array from a WebFigure

Work with MATLAB Image Data

```
In this section...

"For More Comprehensive Examples" on page 6-3

"Working with Images" on page 6-3
```

For More Comprehensive Examples

This section contains code snippets intended to demonstrate specific functionality related to working with figure and image data.

To see these snippets in the context of more fully-functional multi-step examples, see the "Use MATLAB Compiler SDK Web Example Guide".

Working with Images

Getting Encoded Image Bytes from an Image in a Component

```
public byte[] getByteArrayFromDeployedComponent()
    Object[] byteImageOutput = null;
    MWNumericArray numericImageByteArray = null;
    try
    {
        byteImageOutput =
            deployment.getImageDataOrientation(
                        //Number Of Outputs
                500.
                        //Heiaht
                500,
                        //Width
                30.
                        //Elevation
                        //Rotation
                30,
                "png"
                        //Image Format
            );
        numericImageByteArray =
              (MWNumericArray)byteImageOutput[0];
        return numericImageByteArray.getByteData();
    finally
```

```
MWArray.disposeArray(byteImageOutput);
    }
}
Getting a Buffered Image in a Component
public byte[] getByteArrayFromDeployedComponent()
    Object[] byteImageOutput = null;
    MWNumericArray numericImageByteArray = null;
    try
    {
        byteImageOutput =
            deployment.getImageDataOrientation(
                        //Number Of Outputs
                500,
                        //Height
                500,
                        //Width
                        //Elevation
                30.
                30,
                        //Rotation
                "png"
                        //Image Format
            );
        numericImageByteArray =
                 (MWNumericArray)byteImageOutput[0];
        return numericImageByteArray.getByteData();
    finally
        MWArray.disposeArray(byteImageOutput);
}
public BufferedImage getBufferedImageFromDeployedComponent()
    try
    {
        byte[] imageByteArray =
               getByteArrayFromDeployedComponent()
        return ImageIO.read
                (new ByteArrayInputStream(imageByteArray));
    catch(IOException io ex)
        io ex.printStackTrace();
```

}

Creating Scalable Web Applications Using RMI

- "Use Remote Method Invocation (RMI)" on page 7-2
- "RMI Prerequisites" on page 7-3
- "Run Client and Server on Same Machine" on page 7-4
- "Run Client and Server on Separate Machines" on page 7-8
- "Why Use Native Cell Arrays and Struct Arrays?" on page 7-9
- "Native Data Marshaling Prerequisites" on page 7-11
- "Use Native Java Cell and Struct Arrays" on page 7-12
- "Additional RMI Examples" on page 7-16

Use Remote Method Invocation (RMI)


You can expand your application's throughput capacity by taking advantage of RMI, the Java native remote procedure call (RPC) mechanism. The way the MATLAB Compiler SDK product implements RMI technology provides for automatic generation of interface code to enable components to start in separate processes, on one or more computers, making your applications scalable and adaptable to future performance demands.

You can use RMI in the following ways:

- Run a client and server on a single machine
- · Run a client and server on separate machines

Tip While running on UNIX, ensure you use: as the path separator in calls to java and javac.

; is used as a path separator only on Windows.



RMI Prerequisites

This section describes the prerequisites needed prior to using RMI.

Ensure You Have the Required Products

The following products must be installed at their recommended release levels.

- MATLAB, MATLAB Compiler, MATLAB Compiler SDK
- Java Development Kit (JDK)

Ensure you have a JDK installed on your system. You can download OpenJDK from https://adoptopenjdk.net/.

Note You should be using the same major version of Java that ships with MATLAB. To find out what version of Java MATLAB is running, enter the following MATLAB command:

version - java

Ensure Your Web Server Is Java Compliant

In order to run this example, your Web server must be capable of running accepted Java frameworks like J2EE.

Install the javabuilder.jar Library

Ensure that the javabuilder.jar library (matlabroot/toolbox/javabuilder.jar) has been installed into your Web server's common library folder.

Run Client and Server on Same Machine

The following example shows how to run two separate processes to initialize MATLAB struct arrays.

Note You do not need the MATLAB Runtime installed on the client side. Return values from the MATLAB Runtime can be automatically converted using the marshalOutputs Boolean in the RemoteProxy class. See the Javadoc API documentation for details at matlabroot/help/toolbox/javabuilder/MWArrayAPI.

1 Compile the Java package by issuing the following command at the MATLAB command prompt:

```
mcc -W 'java:dataTypesComp,dataTypesClass' createEmptyStruct.m updateField.m -v
```

createEmptyStruct.m

updateField.m

```
function FinalStruct = updateField(st,field_name)

fprintf('\nEVENT 3: Partially initialized structure as received by MATLAB:\n\n');

disp(st);

fprintf('Address field as initialized from the client:\n\n');

disp(st.Address);

fprintf('################################\n');

fprintf(['\nEVENT 4: Updating ''', field_name, ''' field before sending the structure back to the JAVA client:\n\n']

st.(field_name) = 'MathWorks';

FinalStruct = st;

disp(FinalStruct);

fprintf('\n###############################\n');
```

Compile the server Java code by issuing the following javac command at your system command prompt. Ensure there are no spaces between javabuilder.jar; and directory_containing_package. javac -classpath matlabroot\toolbox\javabuilder\jar\javabuilder.jar; directory_cont

You can find DataTypesServer.java in:

matlabroot\toolbox\javabuilder\Examples\RMIExamples
\DataTypes\DataTypesDemoJavaApp

Compile the client Java code by issuing the following javac command at your system command prompt. Ensure there are no spaces between javabuilder.jar; and directory containing package.

javac -classpath matlabroot\toolbox\javabuilder\jar\javabuilder.jar; directory_cont

- **4** Run the client and server as follows:
 - a Open two command windows.
 - b If running Windows, ensure that matlabroot/runtime/arch is defined on the system path. If running UNIX, ensure LD_LIBRARY_PATH and DYLD_LIBRARY_PATH are set properly.
 - Run the server by issuing the following java command at the system command prompt. Ensure there are no spaces between dataTypesComp.jar; and matlabroot.

java -classpath .;directory_containing_package\dataTypesComp.jar; matlabroot\to

d Run the client by issuing the following *java* command at the system command prompt. Ensure there are no spaces between dataTypesComp.jar; and *matlabroot*.

java -classpath .;directory_containing_package\dataTypesComp.jar; matlabroot\to

You can find DataTypesClient.java in: matlabroot\toolbox\javabuilder \Examples\RMIExamples\DataTypes\DataTypesDemoJavaApp.

If successful, the following output appears in the Command Window running the server:

If successful, the following output appears in the Command Window running the client:

```
Running the client application!!
            EVENT 2: Initialized structure as received in client applications:
                   Name: []
                Address: []
            Updating the 'Address' field to :
                Street: '3, Apple Hill Drive'
                 City: 'Natick'
State: 'MA'
                   Zip: '01760'
            ######################################
            EVENT 5: Final structure as received by client:
                   Name: 'The MathWorks'
                Address: [1x1 struct]
            Address field:
                Street: '3, Apple Hill Drive'
                 City: 'Natick'
State: 'MA'
                   Zip: '01760'
```

Run Client and Server on Separate Machines

To implement RMI with a client on one machine and a server on another, you must:

- 1 Change how the server is bound to the system registry.
- **2** Redefine how the client accesses the server.

After this is done, follow the steps in "Run Client and Server on Same Machine" on page 7-4.

Why Use Native Cell Arrays and Struct Arrays?

In Java, there is no direct representation available for MATLAB struct arrays and cell arrays.

As a result, when an instance of MWStructArray or MWCellArray is converted to a Java native type using the toArray() method, the output is a multi-dimensional Object array which can be difficult to process.

When you use MATLAB Compiler SDK packages with RMI, however, you have control over how the server sends the results of MATLAB function calls back to the client. The server can be set to marshal the output to the client as an MWArray (com.mathworks.toolbox.javabuilder package) sub-type or as a Java native data type. The Java native data type representation of MWArray subtypes is obtained by invoking the toArray() method by the server.

Using Java native representations of MATLAB struct and cell arrays is recommended if both of these are true:

- You have MATLAB functions on a server with MATLAB struct or cell data types as inputs or outputs
- You do not want or need to install MATLAB Runtime on your client machines

Using Native Types Does Not Require a Client-Side MATLAB Runtime

The classes in the com.mathworks.extern.java package (in javabuilder.jar) do not need a MATLAB Runtime. The names of the classes in this package are the same as those in com.mathworks.toolbox.javabuilder — allowing the end-user to easily create instances of com.mathworks.extern.java.MWStructArray or com.mathworks.extern.java.MWCellArray that work the same as the like-named classes in com.mathworks.toolbox.javabuilder — on a machine that does not have a MATLAB Runtime.

The availability of a MATLAB Runtime on the client machine dictates how the server should be set for marshaling MATLAB functions, since the MWArray class hierarchy can be used only with a MATLAB Runtime. If the client machine does not have a MATLAB Runtime available, the server returns the output of toArray() for cell or struct arrays as

 $instances\ of\ com.\ mathworks.\ extern.\ java.\ MWStructArray\ or\ com.\ mathworks.\ extern.\ java.\ MWCellArray.$

Native Data Marshaling Prerequisites

Even though client machines don't need to have a MATLAB Runtime, they do need to have javabuilder.jar since it contains the com.mathworks.extern.java package.

Please refer to the Javadoc (matlabroot/help/toolbox/javabuilder/MWArrayAPI) for more information about classes in all MATLAB Compiler SDK Java packages.

Use Native Java Cell and Struct Arrays

Before You Run the Example

Before you run this example, note the following:

- This example demonstrates how to implement RMI when the client and the server are running on the same machine. See "Run Client and Server on Separate Machines" on page 7-8 if you would like to do otherwise.
- On UNIX, use: as the path separator in calls to java and javac. Use; as a path separator on Windows.
- Only update the server system path with the location of the MATLAB Runtime. The client does not need access to the MATLAB Runtime.
- This example is shipped in the matlab\toolbox\javabuilder\Examples \RMIExamples\NativeCellStruct directory.
- Ensure that:
 - On Windows systems, *matlabroot*/runtime/arch is on the system path.
 - On UNIX systems, LD_LIBRARY_PATH and DYLD_LIBRARY_PATH are set properly. See "MATLAB Runtime Path Settings for Run-Time Deployment" on page 4-4 for further information on setting the path.

Running the Example

Note Be sure to enter the following as single, unbroken commands.

1 Use the following mcc command to build the package:

2 Compile the server's Java code:

javac -classpath matlabroot\toolbox\javabuilder\jar\javabuilder.jar; directory_containing_package\dataTypesComp.jar NativeCellStructServer.java

3 Compile the client's Java code:

```
javac -classpath matlabroot\toolbox\javabuilder\jar\javabuilder.jar;
directory_containing_package\dataTypesComp.jar
NativeCellStructClient.java
```

- Prepare to run the server and client applications by opening two command windows —one for client and one for server.
- **5** Run the server:

```
java -classpath .;directory_containing_package\dataTypesComp.jar;
    matlabroot\toolbox\javabuilder\jar\javabuilder.jar
-Djava.rmi.server.codebase="file:///matlabroot/toolbox/javabuilder/
jar/javabuilder.jar file:///
directory_containing_package/dataTypesComp.jar"
NativeCellStructServer
```

6 Run the client:

java -classpath .;directory_containing_package\dataTypesComp.jar;
matlabroot\toolbox\javabuilder\jar\javabuilder.jar NativeCellStructClient

- 7 If your application has run successfully, the output will display as follows:
 - Server output:

```
Please wait for the server registration notification.

Server registered and running successfully!!

EVENT 1: Initializing the structure on server and sending it to client:

Initialized empty structure:

Name: ' '
Address: []
```



```
EVENT 3: Partially initialized structure as received by server:

Name: ' '
Address: [1x1 struct]

Address field as initialized from the client:

Street: '3, Apple Hill Drive'
```

City: 'Natick' State: 'MA' Zip: '01760'

EVENT 4: Updating 'Name' field before sending the structure back to the client

Name: 'The MathWorks' Address: [1x1 struct]

· Client output:

Running the client application!!

EVENT 2: Initialized structure as received in client applications:

1x1 struct array with fields:
 Name
 Address

Updating the 'Address' field to :

1x1 struct array with fields:
 Street
 City
 State
 Zip

EVENT 5: Final structure as received by client:

1x1 struct array with fields:
 Name
 Address

Address field:

```
1x1 struct array with fields:
   Street
   City
   State
   Zip
```

Additional RMI Examples

For more examples of RMI implementation, see the examples in matlabroot/toolbox/javabuilder/Examples/RMIExamples.

Troubleshooting

Common MATLAB Compiler SDK Error Messages

Exception in thread "main" java.lang.UnsatisfiedLinkError: Failed to find the library mclmcrrt712.dll, required by MATLAB Compiler SDK, on java.library.path

Install the MATLAB Runtime or add it to the MATLAB path.

Failed to find the library <library_name>, required by MATLAB Compiler SDK, on java.library.path.

This error commonly occurs on Linux or Mac systems if the LD_LIBRARY_PATH variable is not set.

See "MATLAB Runtime Path Settings for Development and Testing" on page 4-2 and "MATLAB Runtime Path Settings for Run-Time Deployment" on page 4-4.

javac is not recognized as an internal or external command, operable program or batch file.

This is a common error when the javac executable (javac.exe), installed with Java, is not on your system PATH.

Edit your system environment variables and add your Java installation folder to the PATH variable.

Java packages generated using the LibraryCompiler app that serialize and deserialize MathWorks Java classes will throw an exception or hang when using serialization filtering in Java 8.

MathWorks® Java classes need to be on the filter pattern list of the serialization filtering feature of Java 8 so that they can be passed to the method java.io.ObjectInputStream.filterCheck(). This will prevent an application using the Java package from thowing an exception or from hanging. To fix the issue, set the following system properties at the command line:

```
jdk.serialFilter=com.mathworks.**
sun.rmi.registry.registryFilter=com.mathworks.**
```

Reference Information for Java

- "Requirements for the MATLAB Compiler SDK Java Target" on page 9-2
- "Rules for Data Conversion Between Java and MATLAB" on page 9-4
- "Programming Interfaces Generated MATLAB Compiler SDK" on page 9-9
- "Share MATLAB Runtime Instances" on page 9-14
- "MWArray Class Specification" on page 9-15

Requirements for the MATLAB Compiler SDK Java Target

In this section...

"System Requirements" on page 9-2

"Path Modifications Required for Accessibility" on page 9-2

"Limitations of the MATLAB Compiler SDK Java Target" on page 9-3

System Requirements

System requirements and restrictions on use of the MATLAB Compiler SDK Java target are as follows:

- The MATLAB Compiler product must be installed.
- Java Development Kit must be installed.
- Java Runtime Environment that is used by MATLAB and MATLAB Runtime

Note You should be using the same major version of Java that ships with MATLAB. To find out what version of Java MATLAB is running, enter the following MATLAB command:

version -java

Path Modifications Required for Accessibility

In order to use some screen-readers or assistive technologies, such as JAWS, you must add the following DLLs to your Windows path:

matlabroot\sys\java\jre\arch\jre\bin\JavaAccessBridge.dll
matlabroot\sys\java\jre\arch\jre\bin\WindowsAccessBridge.dll

You may not be able to use such technologies without doing so.

Limitations of the MATLAB Compiler SDK Java Target

MATLAB Java External Interface

JAR files created by MATLAB Compiler SDK cannot be loaded back into MATLAB with the MATLAB Java External Interface.

MATLAB Objects

The MATLAB Compiler SDK product's Java target does not support MATLAB object data types. MATLAB objects cannot "pass" the MATLAB/Java boundary. However, you are free to use objects in your MATLAB code.

Rules for Data Conversion Between Java and MATLAB

In this section...

"Java to MATLAB Conversion" on page 9-4

"MATLAB to Java Conversion" on page 9-6

"Unsupported MATLAB Array Types" on page 9-8

Java to MATLAB Conversion

The following table lists the data conversion rules for converting Java data types to MATLAB types.

Note The conversion rules apply to scalars, vectors, matrices, and multidimensional arrays of the types listed.

The conversion rules apply not only when calling your own methods, but also when calling constructors and factory methods belonging to the MWArray classes.

When calling an MWArray class method constructor, supplying a specific data type causes the compiler to convert to that type instead of the default.

Java to MATLAB Conversion Rules

Java Type	MATLAB Type
double	double
float	single
byte	int8
int	int32
short	int16
long	int64
char	char
boolean	logical
java.lang.Double	double
java.lang.Float	single
java.lang.Byte	int8
java.lang.Integer	int32
java.lang.Long	int64
java.lang.Short	int16
java.lang.Number	double
	Note Subclasses of java.lang.Number not listed above are converted to double.
java.lang.Boolean	logical
java.lang.Character	char

Java Type	MATLAB Type
java.lang.String	char
	Note A Java string is converted to a 1-by-N array of char with N equal to the length of the input string.
	An array of Java strings (String[]) is converted to an M-by-N array of char, with M equal to the number of elements in the input array and N equal to the maximum length of any of the strings in the array.
	Higher dimensional arrays of String are converted similarly.
	In general, an N-dimensional array of String is converted to an N +1 dimensional array of char with appropriate zero padding where supplied strings have different lengths.

MATLAB to Java Conversion

The following table lists the data conversion rules for converting MATLAB data types to Java types.

Note The conversion rules apply to scalars, vectors, matrices, and multidimensional arrays of the types listed.

MATLAB to Java Conversion Rules

MATLAB Type	Java Type (Primitive)	Java Type (Object)
cell	Not applicable	Object
		Note Cell arrays are constructed and accessed as arrays of MWArray.
structure	Not applicable	0bject
		Note Structure arrays are constructed and accessed as arrays of MWArray.
char	char	java.lang.Character
double	double	java.lang.Double
single	float	java.lang.Float
int8	byte	java.lang.Byte
int16	short	java.lang.Short
int32	int	java.lang.Integer
int64	long	java.lang.Long
uint8	byte	java.lang.Byte
		Java has no unsigned type to represent the uint8 used in MATLAB. Construction of and access to MATLAB arrays of an unsigned type requires conversion.
uint16	short	java.lang.short
		Java has no unsigned type to represent the uint16 used in MATLAB. Construction of and access to MATLAB arrays of an unsigned type requires conversion.

MATLAB Type	Java Type (Primitive)	Java Type (Object)
uint32	int	java.lang.Integer
		Java has no unsigned type to represent the uint32 used in MATLAB. Construction of and access to MATLAB arrays of an unsigned type requires conversion.
uint64	long	java.lang.Long
		Java has no unsigned type to represent the uint64 used in MATLAB. Construction of and access to MATLAB arrays of an unsigned type requires conversion.
logical	boolean	java.lang.Boolean
Function handle	Not supported	
Java class	Not supported	
User class	Not supported	

Unsupported MATLAB Array Types

Java has no unsigned types to represent the uint8, uint16, uint32, and uint64 types used in MATLAB. Construction of and access to MATLAB arrays of an unsigned type requires conversion.

Programming Interfaces Generated MATLAB Compiler SDK

In this section...

"APIs Based on MATLAB Function Signatures" on page 9-9

"Standard API" on page 9-10

"mlx API" on page 9-11

"Code Fragment: Signatures Generated for the myprimes Example" on page 9-12

APIs Based on MATLAB Function Signatures

The compiler generates two kinds of interfaces to handle MATLAB function signatures.

A standard signature in Java

This interface specifies input arguments for each overloaded method as one or more input arguments of class <code>java.lang.Object</code> or any subclass (including subclasses of MWArray). The standard interface specifies return values, if any, as a subclass of MWArray.

mlx API

This interface allows the user to specify the inputs to a function as an Object array, where each array element is one input argument. Similarly, the user also gives the mlx interface a preallocated Object array to hold the outputs of the function. The allocated length of the output array determines the number of desired function outputs.

The mlx interface may also be accessed using java.util.List containers in place of Object arrays for the inputs and outputs. Note that if List containers are used, the output List passed in must contain a number of elements equal to the desired number of function outputs.

For example, this would be incorrect usage:

```
java.util.List outputs = new ArrayList(3);
myclass.myfunction(outputs, inputs); // outputs 0 elements!
```

And this would be the correct usage:

```
java.util.List outputs = Arrays.asList(new Object[3]);
myclass.myfunction(outputs, inputs); // list has 3 elements
```

Typically you use the standard interface when you want to call MATLAB functions that return a single array. In other cases you probably need to use the mlx interface.

Standard API

The standard calling interface returns an array of one or more MWArray objects.

The standard API for a generic function with none, one, more than one, or a variable number of arguments, is shown in the following table.

Arguments	API to Use
Generic MATLAB function	<pre>function [Out1, Out2,, varargout] = foo(In1 InN, varargin)</pre>
API if there are no input arguments	<pre>public Object[] foo(int numArgsOut)</pre>
API if there is one input argument	<pre>public Object[] foo(int numArgsOut, Object In1)</pre>
API if there are two to N input arguments	<pre>public Object[] foo(int numArgsOut, Object In1, Object In2, Object InN)</pre>
API if there are optional arguments, represented by the varargin argument	<pre>public Object[] foo(int numArgsOut, Object in1, Object in2, , Object InN, Object varargin)</pre>

, In2, ...

Details about the arguments for these samples of standard signatures are shown in the following table.

Argument	Description	Details About Argument
numArgsOut	Number of outputs	An integer indicating the number of outputs you want the method to return. To return no arguments, omit this argument. The value of numArgsOut must be less than or equal to the MATLAB function nargout. The numArgsOut argument must always be the
		first argument in the list.
In1, In2,InN	Required input arguments	All arguments that follow numArgsOut in the argument list are inputs to the method being called. Specify all required inputs first. Each required input must be of class MWArray or any class derived from MWArray.
varargin	Optional inputs	You can also specify optional inputs if your MATLAB code uses the varargin input: list the optional inputs, or put them in an Object[] argument, placing the array last in the argument list.
Out1, Out2,OutN	Output arguments	With the standard calling interface, all output arguments are returned as an array of MWArrays.

mlx API

For a function with the following structure:

The compiler generates the following API, as the ${\tt mlx}$ interface:

Code Fragment: Signatures Generated for the myprimes Example

For a specific example, look at the myprimes method. This method has one input argument, so the compiler generates three overloaded methods in Java.

When you add myprimes to the class myclass and build the class, the compiler generates the myclass.java file. A fragment of myclass.java is listed to show overloaded implementations of the myprimes method in the Java code.

The standard interface specifies inputs to the function within the argument list and outputs as return values. The second implementation demonstrates the feval interface, the third implementation shows the interface to be used if there are no input arguments, and the fourth shows the implementation to be used if there is one input argument. Rather than returning function outputs as a return value, the feval interface includes both input and output arguments in the argument list. Output arguments are specified first, followed by input arguments.

```
/* mlx interface - List version */
public void myprimes(List lhs, List rhs) throws MWException
    (implementation omitted)
/* mlx interface - Array version */
public void myprimes(Object[] lhs, Object[] rhs)
                                        throws MWException
{
    (implementation omitted)
/* Standard interface - no inputs*/
public Object[] myprimes(int nargout) throws MWException
  {
      (implementation omitted)
/* Standard interface - one input*/
public Object[] myprimes(int nargout, Object n)
                                      throws MWException
  {
      (implementation omitted)
  }
```

See "APIs Based on MATLAB Function Signatures" on page 9-9 for details about the interfaces.

Share MATLAB Runtime Instances

In this section...

"What Is a Singleton MATLAB Runtime?" on page 9-14

"Advantages and Disadvantages of Using a Singleton" on page 9-14

What Is a Singleton MATLAB Runtime?

You create an instance of the MATLAB Runtime that can be shared among all subsequent class instances within a component. This is commonly called a shared MATLAB Runtime instance or a Singleton runtime.

Advantages and Disadvantages of Using a Singleton

In most cases, a singleton MATLAB Runtime will provide many more advantages than disadvantages. Following are examples of when you might and might not create a shared MATLAB Runtime instance.

When You Should Use a Singleton

If you have multiple users running from a specific instance of MATLAB, using a singleton will most likely:

- Utilize system memory more efficiently
- Decrease MATLAB Runtime start-up or initialization time

When You Might Avoid Using a Singleton

Using a singleton may not benefit you if your application uses a large number of global variables. This causes crosstalk.

MWArray Class Specification

For complete reference information about the MWArray class hierarchy, see com.mathworks.toolbox.javabuilder.MWArray, which is in the matlabroot/help/toolbox/javabuilder/MWArrayAPI/folder.

Note For *matlabroot*, substitute the MATLAB root folder on your system. Type matlabroot to see this folder name.

Functions — Alphabetical List

mcrinstaller

Display version and location information for MATLAB Runtime installer corresponding to current platform

Syntax

[INSTALLER_PATH, MAJOR, MINOR, PLATFORM] = mcrinstaller;

Description

Displays information about available MATLAB Runtime installers using the format: [INSTALLER PATH, MAJOR, MINOR, PLATFORM] = mcrinstaller; where:

- *INSTALLER PATH* is the full path to the installer for the current platform.
- *MAJOR* is the major version number of the installer.
- MINOR is the minor version number of the installer.
- *PLATFORM* is the name of the current platform (returned by COMPUTER(arch)).

If no MATLAB Runtime installer is found, you are prompted to download an installer using the command compiler.runtime.download.

Note You must distribute the MATLAB Runtime library to your end users to enable them to run applications developed with MATLAB Compiler or MATLAB Compiler SDK.

See "Install and Configure the MATLAB Runtime" for more information about the MATLAB Runtime installer.

Examples

Find MATLAB Runtime Installer Location

Display the location of MATLAB Runtime installers for a particular platform. This example shows output for a win64 system. The release number is called R20xxx indicating the release for which the MATLAB Runtime installer has been downloaded.

mcrinstaller

C:\Program Files\MATLAB\R20xxx\toolbox\compiler\deploy\win64\MCR_R20xxx_win64_installe

For example, for R2018b, the path would be:

C:\Program Files\MATLAB\R2018b\toolbox\compiler\deploy\win64\MCR_R2018b_win64_installe

Introduced in R2009a

mcrversion

Determine version of installed MATLAB Runtime

Syntax

```
[major, minor] = mcrversion;
```

Description

The MATLAB Runtime version number consists of two digits, separated by a decimal point. This function returns each digit as a separate output variable: [major, minor] = mcrversion; Major and minor are returned as integers.

If the version number ever increases to three or more digits, call mcrversion with more outputs, as follows:

```
[major, minor, point] = mcrversion;
```

At this time, all outputs past "minor" are returned as zeros.

Typing only mcrversion will return the major version number only.

Examples

```
mcrversion
ans =
7
```

Introduced in R2008a

waitForFigures

Block execution of a calling program as long as figures created in encapsulated MATLAB code are displayed

Syntax

objName.waitForFigures();

Description

waitForFigures() blocks execution of a calling program as long as figures created in encapsulated MATLAB code are displayed. Typically you use waitForFigures when:

- There are one or more figures open that were created by a Java class created by the MATLAB Compiler SDK product.
- The method that displays the graphics requires user input before continuing.
- The method that calls the figures was called from main() in a console program.

When waitForFigures is called, execution of the calling program is blocked if any figures created by the calling object remain open.

Caution Use care when calling the waitForFigures method. Calling this method from an interactive program like Microsoft® Excel® can hang the application. Call this method *only* from console-based programs.

See Also

Topics

"Execution of Applications that Create Figures" on page 2-57

Introduced before R2006a