

Deep Learning Toolbox™ Release Notes



MATLAB®



How to Contact MathWorks



Latest news: www.mathworks.com
Sales and services: www.mathworks.com/sales_and_services
User community: www.mathworks.com/matlabcentral
Technical support: www.mathworks.com/support/contact_us



Phone: 508-647-7000



The MathWorks, Inc.
1 Apple Hill Drive
Natick, MA 01760-2098

Deep Learning Toolbox™ Release Notes

© COPYRIGHT 2005–2020 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See www.mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

Patents

MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

Experiment Manager: Design and run experiments to train deep learning networks	1-2
Deep Network Designer: Train networks and generate MATLAB code ...	1-2
Deep Network Designer: Easily import pretrained networks for transfer learning	1-2
Deep Network Designer: Import and export networks with multiple inputs or multiple outputs	1-3
Pretrained Networks: Perform transfer learning with DarkNet-19 and DarkNet-53 pretrained convolutional neural networks	1-3
Network Architectures: Load untrained versions of common network architectures	1-3
Deep Learning Data Sets: Explore data sets used for deep learning	1-3
Conditional Generative Adversarial Networks: Train GANs using data labels and other attributes	1-3
Generative Adversarial Networks: Monitor GAN training progress and identify common failure modes	1-4
Image Captioning: Train networks that generate textual captions for images using attention	1-4
Multi-label Classification: Define and train networks for multi-label classification	1-4
Gated Recurrent Units: Train networks for sequence data using gated recurrent unit (GRU) layers	1-4
Global Max Pooling: Reduce network size and help prevent overfitting using global max pooling layers	1-4
Custom Training Loops: Specify networks with 3-D layers and networks with multiple inputs or outputs	1-5
Custom Training Loops: Specify custom layers with custom backward functions	1-5

Automatic Differentiation: New deep learning operations	1-5
Training Options: Edit training option properties	1-6
Deep Learning Validation: Access final validation accuracy, loss, and RMSE after training	1-6
Network Plotting: Plot series networks	1-6
TensorFlow-Keras Support: Import networks with multiple inputs and multiple outputs	1-6
TensorFlow-Keras Support: Import GRU layers, 2-D global max pooling layers, and PReLU advanced activation layers from TensorFlow-Keras	1-7
ONNX Support: Import and export networks with multiple inputs and multiple outputs	1-7
ONNX Support: Import and export networks that include exponential linear unit (ELU) layers, GRU layers, and 2-D global max pooling layers	1-7
Pretrained Networks: Use SqueezeNet without installing support package	1-7
Deep Learning Examples: Explore deep learning workflows	1-7
predict Function: Improved performance for dlnetwork inference	1-8
Functionality being removed or changed	1-9
rmspropupdate squared gradient decay factor default is 0.9	1-9
sequenceInputLayer ignores padding values when normalizing	1-9
maxpool indices output argument changes shape and data type	1-9

R2019b

Deep Learning Customization: Define and train complex networks (including GANs) using custom training loops, automatic differentiation, shared weights, and custom loss functions	2-2
Generative Adversarial Networks: Create and train generative adversarial networks (GANs) for image generation	2-4
Siamese Networks: Create and train Siamese networks for image comparison and dimensionality reduction	2-4
Data Preprocessing: Improve training performance using different data normalization options	2-4

Visualization: Map strongly activating features of input data using occlusion	2-5
Visualization: Visualize the features learned by a DAG network using deep dream	2-5
Multi-Input, Multi-Output Networks: Create and train networks with multiple inputs and multiple outputs	2-5
Long Short-Term Memory Networks: Pad or truncate sequences on the left	2-5
Long Short-Term Memory Networks: Compute intermediate layer activations	2-6
ONNX Support: Export networks that combine CNN and LSTM layers and networks that include 3-D CNN layers to ONNX format	2-6
Global Average Pooling: Reduce network size and help prevent overfitting using global average pooling layers	2-6
Cropping: Crop 2-D and 3-D input data to size of reference feature map	2-6
Deep Learning Examples: Explore deep learning workflows	2-6
Functionality being removed or changed	2-7
AverageImage property of imageInputLayer and image3dInputLayer will be removed	2-7
imageInputLayer and image3dInputLayer, by default, use channel-wise normalization	2-7
sequenceInputLayer, by default, uses channel-wise zero-center normalization	2-7

R2019a

Deep Network Designer: Create networks for computer vision and text applications	3-2
Deep Network Designer: Generate MATLAB code that recreates your network	3-2
Convolutions for Image Sequences: Create LSTM networks for video classification and gesture recognition	3-2
Layer Initialization: Initialize layer weights and biases using initializers or a custom function	3-2
Grouped Convolutions: Create efficient deep learning networks with grouped and channel-wise convolutions	3-3

3-D Support: New layers enable deep learning with 3-D data	3-3
Custom Layers: Create custom layers with multiple inputs or multiple outputs	3-4
Deep Learning Acceleration: Optimize deep learning applications using MEX functions	3-4
Pretrained Networks: Perform transfer learning with NASNet-Large, NASNet-Mobile, MobileNet-v2, ShuffleNet, Xception, and Places365-GoogLeNet pretrained convolutional neural networks	3-4
Deep Learning Layers: Hyperbolic tangent and exponential linear unit activation layers	3-4
Deep Learning Visualization: Investigate network predictions using class activation mapping	3-5
Deep Learning Examples: Explore deep learning workflows	3-5
Functionality being removed or changed	3-6
Glorot is default weights initialization for convolution, transposed convolution, and fully connected layers	3-6
Glorot is default input weights initialization for LSTM and BiLSTM layers	3-6
Orthogonal is default recurrent weights initialization for LSTM and BiLSTM layers	3-6
Custom layers have new properties NumInputs, InputNames, NumOutputs, and OutputNames	3-6
Cropping property of TransposedConvolution2DLayer will be removed ...	3-6
matlab.io.datastore.MiniBatchable is not recommended for custom image preprocessing	3-7
matlab.io.datastore.BackgroundDispatchable and matlab.io.datastore.PartitionableByIndex are not recommended	3-7

R2018b

Renamed Product: Neural Network Toolbox renamed to Deep Learning Toolbox	4-2
Deep Network Designer: Edit and build deep learning networks	4-2
ONNX Support: Import and export models using the ONNX model format for interoperability with other deep learning frameworks	4-3
Network Analyzer: Visualize, analyze, and find problems in network architectures before training	4-3
LSTM Network Validation: Validate networks for time series data automatically during training	4-3

Network Assembly: Assemble networks from imported layers and weights without training	4-3
Output Layer Validation: Verify custom output layers for validity, GPU compatibility, and correctly defined gradients	4-4
Visualization: Investigate network predictions using confusion matrix charts	4-4
Dilated Convolution: Change the dilation factor of convolutional layers to enhance prediction accuracy for tasks such as semantic segmentation	4-4
Sequence Mini-Batch Datastores: Develop datastores for sequence, time series, and signal data	4-4
Pretrained Networks: Perform transfer learning with ResNet-18 and DenseNet-201 pretrained convolutional neural networks	4-4
TensorFlow-Keras: Import LSTM and BiLSTM layers from TensorFlow-Keras	4-5
Caffe Importer: Import directed acyclic graph networks from Caffe	4-5
LSTM Layer Activation Functions: Specify state and gate activation functions	4-5
Deep Learning: New network layers	4-5
Image Data Augmenter: Additional options for augmenting and visualizing images	4-6
Deep Learning Examples: Explore deep learning workflows	4-6
Functionality being removed or changed	4-7
'ValidationPatience' training option default is Inf	4-7
ClassNames property of ClassificationOutputLayer will be removed	4-7
'ClassNames' option of importKerasNetwork, importCaffeNetwork, and importONNXNetwork will be removed	4-7
Different file name for checkpoint networks	4-7

R2018a

Long Short-Term Memory (LSTM) Networks: Solve regression problems with LSTM networks and learn from full sequence context using bidirectional LSTM layers	5-2
Deep Learning Optimization: Improve network training using Adam, RMSProp, and gradient clipping	5-2

Deep Learning Data Preprocessing: Read data and define preprocessing operations efficiently for training and prediction	5-2
Deep Learning Layer Validation: Check layers for validity, GPU compatibility, and correctly defined gradients	5-3
Directed Acyclic Graph (DAG) Networks: Accelerate DAG network training using multiple GPUs and compute intermediate layer activations	5-3
Confusion Matrix: Plot confusion matrices for categorical labels	5-3
Multispectral Deep Learning: Train convolutional neural networks on multispectral images	5-3
Directed Acyclic Graph (DAG) Network Editing: Replace a layer in a layer graph more easily	5-3
Pretrained Networks: Accelerate transfer learning by freezing layer weights	5-3
Pretrained Networks: Transfer learning with pretrained SqueezeNet and Inception-ResNet-v2 convolutional neural networks	5-4
Deep Learning Network Analyzer: Visualize, analyze, and find issues in network architectures	5-4
ONNX Support: Import and export models using the ONNX model format for interoperability with other deep learning frameworks	5-4
Deep Learning Speech Recognition: Train a simple deep learning model to detect speech commands	5-4
Parallel Deep Learning Workflows: Explore deep learning with multiple GPUs locally or in the cloud	5-5
Deep Learning Examples: Explore deep learning applications	5-5
Functionality Being Removed or Changed	5-5

R2017b

Directed Acyclic Graph (DAG) Networks: Create deep learning networks with more complex architecture to improve accuracy and use many popular pretrained models	6-2
Long Short-Term Memory (LSTM) Networks: Create deep learning networks with the LSTM recurrent neural network topology for time-series classification and prediction	6-2

Deep Learning Validation: Automatically validate network and stop training when validation metrics stop improving	6-3
Deep Learning Layer Definition: Define new layers with learnable parameters, and specify loss functions for classification and regression output layers	6-3
Deep Learning Training Plots: Monitor training progress with plots of accuracy, loss, validation metrics, and more	6-3
Deep Learning Image Preprocessing: Efficiently resize and augment image data for training	6-4
Bayesian Optimization of Deep Learning: Find optimal settings for training deep networks (Requires Statistics and Machine Learning Toolbox)	6-4
GoogLeNet Pretrained Network: Transfer learning with pretrained GoogLeNet convolutional neural network	6-4
ResNet-50 and ResNet-101 Pretrained Networks: Transfer learning with pretrained ResNet-50 and ResNet-101 convolutional neural networks	6-5
Inception-v3 Pretrained Network: Transfer learning with pretrained Inception-v3 convolutional neural network	6-5
Batch Normalization Layer: Speed up network training and reduce sensitivity to network initialization	6-5
Deep Learning: New network layers	6-6
Pretrained Models: Import pretrained CNN models and layers from TensorFlow-Keras	6-6
Functionality Being Removed or Changed	6-6

R2017a

Deep Learning for Regression: Train convolutional neural networks (also known as ConvNets, CNNs) for regression tasks	7-2
Pretrained Models: Transfer learning with pretrained CNN models AlexNet, VGG-16, and VGG-19, and import models from Caffe (including Caffe Model Zoo)	7-2
Deep Learning with Cloud Instances: Train convolutional neural networks using multiple GPUs in MATLAB and MATLAB Distributed Computing Server for Amazon EC2	7-2

Deep Learning with Multiple GPUs: Train convolutional neural networks on multiple GPUs on PCs (using Parallel Computing Toolbox) and clusters (using MATLAB Distributed Computing Server)	7-3
Deep Learning with CPUs: Train convolutional neural networks on CPUs as well as GPUs	7-3
Deep Learning Visualization: Visualize the features ConvNet has learned using deep dream and activations	7-3
table Support: Use data in tables for training of and inference with ConvNets	7-3
Progress Tracking During Training: Specify custom functions for plotting accuracy or stopping at a threshold	7-3
Deep Learning Examples: Get started quickly with deep learning	7-4

R2016b

Deep Learning with CPUs: Run trained CNNs to extract features, make predictions, and classify data on CPUs as well as GPUs	8-2
Deep Learning with Arbitrary Sized Images: Run trained CNNs on images that are different sizes than those used for training	8-2
Performance: Train CNNs faster when using ImageDatastore object	8-2
Deploy Training of Models: Deploy training of a neural network model via MATLAB Compiler or MATLAB Compiler SDK	8-2
generateFunction Method: generateFunction generates code for matrices by default	8-2
alexnet Support Package: Download and use pre-trained convolutional neural network (ConvNet)	8-3

R2016a

Deep Learning: Train deep convolutional neural networks with built-in GPU acceleration for image classification tasks (using Parallel Computing Toolbox)	9-2
---	------------

R2015b

Autoencoder neural networks for unsupervised learning of features using the trainAutoencoder function	10-2
Deep learning using the stack function for creating deep networks from autoencoders	10-2
Improved speed and memory efficiency for training with Levenberg-Marquardt (trainlm) and Bayesian Regularization (trainbr) algorithms	10-2
Cross entropy for a single target variable	10-2

R2015a

Progress update display for parallel training	11-2
--	-------------

R2014b

Bug Fixes

R2014a

Training panels for Neural Fitting Tool and Neural Time Series Tool Provide Choice of Training Algorithms	13-2
Bayesian Regularization Supports Optional Validation Stops	13-2
Neural Network Training Tool Shows Calculations Mode	13-2

R2013b

Function code generation for application deployment of neural network simulation (using MATLAB Coder, MATLAB Compiler, and MATLAB Builder products)	14-2
New Function: genFunction	14-2

Enhanced Tools	14-3
Enhanced multi-timestep prediction for switching between open-loop and closed-loop modes with NARX and NAR neural networks	14-4
Cross-entropy performance measure for enhanced pattern recognition and classification accuracy	14-6
Softmax transfer function in output layer gives consistent class probabilities for pattern recognition and classification	14-6
Automated and periodic saving of intermediate results during neural network training	14-8
Simpler Notation for Networks with Single Inputs and Outputs	14-9
Neural Network Efficiency Properties Are Now Obsolete	14-9

R2013a

Bug Fixes

R2012b

Speed and memory efficiency enhancements for neural network training and simulation	16-2
Speedup of training and simulation with multicore processors and computer clusters using Parallel Computing Toolbox	16-4
GPU computing support for training and simulation on single and multiple GPUs using Parallel Computing Toolbox	16-6
Distributed training of large datasets on computer clusters using MATLAB Distributed Computing Server	16-7
Elliot sigmoid transfer function for faster simulation	16-7
Faster training and simulation with computer clusters using MATLAB Distributed Computing Server	16-8
Load balancing parallel calculations	16-9
Summary and fallback rules of computing resources used from train and sim	16-10

Updated code organization 16-11

R2012a

Bug Fixes

R2011b

Bug Fixes

R2011a

Bug Fixes

R2010b

New Neural Network Start GUI	20-2
New Time Series GUI and Tools	20-2
New Time Series Validation	20-7
New Time Series Properties	20-8
New Flexible Error Weighting and Performance	20-8
New Real Time Workshop and Improved Simulink Support	20-9
New Documentation Organization and Hyperlinks	20-10
New Derivative Functions and Property	20-11
Improved Network Creation	20-11
Improved GUIs	20-12
Improved Memory Efficiency	20-12

Improved Data Sets	20-12
Updated Argument Lists	20-13

R2010a

Bug Fixes

R2009b

Bug Fixes

R2009a

Bug Fixes

R2008b

Bug Fixes

R2008a

New Training GUI with Animated Plotting Functions	25-2
New Pattern Recognition Network, Plotting, and Analysis GUI	25-2
New Clustering Training, Initialization, and Plotting GUI	25-2
New Network Diagram Viewer and Improved Diagram Look	25-3
New Fitting Network, Plots and Updated Fitting GUI	25-3

Simplified Syntax for Network-Creation Functions	26-2
Automated Data Preprocessing and Postprocessing During Network Creation	26-2
Default Processing Settings	26-3
Changing Default Input Processing Functions	26-3
Changing Default Output Processing Functions	26-4
Automated Data Division During Network Creation	26-4
New Data Division Functions	26-5
Default Data Division Settings	26-5
Changing Default Data Division Settings	26-5
New Simulink Blocks for Data Preprocessing	26-5
Properties for Targets Now Defined by Properties for Outputs	26-6

No New Features or Changes

No New Features or Changes

Dynamic Neural Networks	29-2
Time-Delay Neural Network	29-2
Nonlinear Autoregressive Network (NARX)	29-2
Layer Recurrent Network (LRN)	29-2
Custom Networks	29-2
Wizard for Fitting Data	29-2
Data Preprocessing and Postprocessing	29-2
dividevec Automatically Splits Data	29-2
fixunknowns Encodes Missing Data	29-2
removeconstantrows Handles Constant Values	29-3

mapminmax, mapstd, and processpca Are New	29-3
Derivative Functions Are Obsolete	29-3

R14SP3

No New Features or Changes

R2020a

Version: 14

New Features

Bug Fixes

Compatibility Considerations

Experiment Manager: Design and run experiments to train deep learning networks

Create a deep learning experiment to train networks under various initial conditions and compare the results by using the **Experiment Manager** app. For example, you can use deep learning experiments to:

- Sweep through a range of hyperparameter values to train a deep network.
- Compare the results of using different data sets to train a network.
- Test different deep network architectures by reusing the same set of training data on several networks.

The **Experiment Manager** app provides visualization tools such as training plots, confusion matrices, filters to refine your experiment results, and the ability to define custom metrics to evaluate your results. To improve reproducibility, every time that you run an experiment, the **Experiment Manager** app stores a snapshot of your experiment definition. For example, you can use snapshots to track the hyperparameter combinations that produce each of your results.

For more information, see these examples:

- “Create a Deep Learning Experiment for Classification”
- “Create a Deep Learning Experiment for Regression”
- “Evaluate Deep Learning Experiments by Using Metric Functions”
- “Try Multiple Pretrained Networks for Transfer Learning”
- “Experiment with Weight Initializers for Transfer Learning”

Deep Network Designer: Train networks and generate MATLAB code

Train image classification networks using the **Deep Network Designer** app.

The **Deep Network Designer** app now supports importing training and validation data, visualizing data distribution, augmenting images, specifying training options, training networks with progress plots, and exporting trained networks.

For an example showing how to train an image classification network using Deep Network Designer, see “Get Started with Deep Network Designer”.

You can also generate code MATLAB® from the **Deep Network Designer** app. The generated code contains information on the network architecture, training and validation data import, image augmentation, and training options.

For more information, see “Generate MATLAB Code from Deep Network Designer”.

Deep Network Designer: Easily import pretrained networks for transfer learning

Import pretrained networks for transfer learning using the **Deep Network Designer** app. To load a pretrained network, open the **Deep Network Designer** app and select the icon for the desired pretrained network.

Each icon displays key information about the depth, size, number of parameters and input size of the pretrained network. For an example showing how to retrain a pretrained network, see “Transfer Learning with Deep Network Designer”.

Deep Network Designer: Import and export networks with multiple inputs or multiple outputs

Use the **Deep Network Designer** app to import, edit, export, and generate code for networks with multiple input or multiple output layers.

Pretrained Networks: Perform transfer learning with DarkNet-19 and DarkNet-53 pretrained convolutional neural networks

You can now install add-ons for the DarkNet-19 and DarkNet-53 pretrained convolutional neural networks. To download and install the pretrained networks, use the Add-On Explorer. You can also download the networks from MathWorks Deep Learning Toolbox Team. After you install the add-ons, use the `darknet19` and `darknet53` functions to load the networks, respectively.

To retrain a network on a new classification task, follow the steps in “Train Deep Learning Network to Classify New Images” and load the pretrained network you want to use instead of GoogLeNet.

For more information on pretrained neural networks in MATLAB, see “Pretrained Deep Neural Networks”.

Network Architectures: Load untrained versions of common network architectures

You can now load untrained versions of the pretrained networks in Deep Learning Toolbox. To load an untrained version of a pretrained network as a layer graph, use the corresponding pretrained network function and set the `'Weights'` option to `'none'`. Loading an untrained version of pretrained networks does not require installing a support package.

For a list of pretrained networks in deep Learning Toolbox, see “Pretrained Deep Neural Networks”.

Deep Learning Data Sets: Explore data sets used for deep learning

For a list of data sets used for different deep learning workflows and how to import them into MATLAB, see “Data Sets for Deep Learning”.

Conditional Generative Adversarial Networks: Train GANs using data labels and other attributes

A conditional generative adversarial network is a type of type of generative adversarial network that also takes advantage of labels, responses, and other attributes during the training process. You can then use the generator of conditional GANs to generate images with specified classes or attributes.

For an example showing how to train a conditional GAN using labeled data, see “Train Conditional Generative Adversarial Network (CGAN)”.

Generative Adversarial Networks: Monitor GAN training progress and identify common failure modes

Training GANs can be a challenging task. To learn how identify common failure modes and for suggestions on how to fix them, see “Monitor GAN Training Progress and Identify Common Failure Modes”. For an example showing how to plot GAN training progress, see “Train Generative Adversarial Network (GAN)”.

Image Captioning: Train networks that generate textual captions for images using attention

Train models with an encoder-decoder architecture for image captioning by using pretrained image classification networks as encoders and recurrent neural network (RNN) that takes the extracted features as input and generates captions as decoders. You can incorporate an *attention mechanism* in the decoder that allows the model to focus on parts of the encoded input while generating the caption.

For an example showing how to train an image captioning network, see “Image Captioning Using Attention”. This example requires Text Analytics Toolbox™.

Multi-label Classification: Define and train networks for multi-label classification

For multi-label classification tasks (where observations can be assigned to more than one independent category), you can train the network using a custom training loop by specifying cross-entropy loss for independent classes. This loss function is also known as binary cross-entropy loss.

To specify cross-entropy loss for independent classes, use the `crossentropy` function and set the 'TargetCategories' option to 'independent'.

For an example showing to how to do multi-label classification for text data, see “Multilabel Text Classification Using Deep Learning”.

Gated Recurrent Units: Train networks for sequence data using gated recurrent unit (GRU) layers

A GRU layer learns dependencies between time steps in time series and sequence data. To include a GRU layer in a layer graph or layer array, use the `gruLayer` function. To apply the GRU operation in a model function used in a custom training loop, use the `gru` function.

For an example showing how to train an image captioning network using gated recurrent units, see “Image Captioning Using Attention”. This example requires Text Analytics Toolbox.

Global Max Pooling: Reduce network size and help prevent overfitting using global max pooling layers

A global max pooling layer performs downsampling by computing the maximum of the spatial dimensions of the input. For 2-D data, create a global max pooling layer with the `globalMaxPooling2dLayer` function. For 3-D data, use the `globalMaxPooling3dLayer` function.

Custom Training Loops: Specify networks with 3-D layers and networks with multiple inputs or outputs

The `dlnetwork` function now supports layer graphs with multiple input or multiple outputs, and layer graphs with the following 3-D layers:

- `convolution3dLayer`
- `transposedConv3dLayer`
- `crop3dLayer`
- `averagePooling3dLayer`
- `globalAveragePooling3dLayer`
- `maxPooling3dLayer`
- `globalMaxPooling3dLayer`

To evaluate a `dlnetwork` object that has multiple inputs or multiple outputs during training or inference, use the `forward` and `predict` functions, respectively. For an example showing how to train a conditional GAN using multi-input networks, see “Train Conditional Generative Adversarial Network (CGAN)”.

To learn more about custom training loops, see “Define Custom Training Loops, Loss Functions, and Networks”.

Custom Training Loops: Specify custom layers with custom backward functions

The `dlnetwork` function now supports layer graphs with custom layers with custom backward functions. Specifying a backward function is optional. Use custom backward functions when the forward function does not support automatic differentiation or when you want to use a specific algorithm for the backward pass.

For a list of layers in Deep Learning Toolbox, see “List of Deep Learning Layers”. For an example showing how to define a custom backward function, see “Specify Custom Layer Backward Function”. For an example showing how to define a custom backward loss function, see “Specify Custom Output Layer Backward Loss Function”.

For more information about defining custom deep learning layers, see “Define Custom Deep Learning Layers”.

Automatic Differentiation: New deep learning operations

Define custom model functions using the following operations:

- Gated recurrent units - Apply gated recurrent unit (GRU) operations using the `gru` function.
- Cross channel normalization - Apply cross channel normalization (also known as local response normalization) using the `crosschannelnorm` function.
- Global average and global max pooling - Apply global average and global max pooling operations using the `avgpool` and `maxpool` functions, respectively, by setting the pooling region size to `'global'`.

- Batch matrix multiplication - Perform matrix multiplication in batches using the `dlmtimes` function.
- Rescaling - Rescale data using the `rescale` function.
- Ceiling and floor operations - Apply the `ceil` and `floor` functions to data in model functions.
- Floating point accuracy - For single and double precision, determine the distance to the next largest floating point number using the `eps` function. Use this value to bound calculations away from zero.

For a list of functions that support automatic differentiation, see “List of Functions with `dlarray` Support”. To learn more about defining and training deep learning models using automatic differentiation, see “Define Custom Training Loops, Loss Functions, and Networks”.

Training Options: Edit training option properties

You can now edit training option properties of `TrainingOptionsSGDM`, `TrainingOptionsADAM`, and `TrainingOptionsRMSProp` objects directly.

For example, to change the mini-batch size after using the `trainingOptions` function, you can edit the `MiniBatchSize` property directly:

```
options = trainingOptions('sgdm');  
options.MiniBatchSize = 64;
```

Deep Learning Validation: Access final validation accuracy, loss, and RMSE after training

Access the final validation metrics after training using the information struct output by `trainNetwork`.

- For classification problems, access the validation loss and accuracy from the `FinalValidationLoss` and `FinalValidationAccuracy` fields of the information struct, respectively.
- For regression problems, access the validation loss and RMSE from the `FinalValidationLoss` and `FinalValidationRMSE` fields of the information struct, respectively.

Network Plotting: Plot series networks

The `plot` function now supports `SeriesNetwork` objects.

TensorFlow-Keras Support: Import networks with multiple inputs and multiple outputs

You can import a Keras network with multiple inputs and multiple outputs. Use `importKerasNetwork` if the network includes input size information for the inputs and loss information for the outputs. Otherwise, use `importKerasLayers`. The `importKerasLayers` function inserts placeholder layers for the inputs and outputs. After importing, you can find and replace the placeholder layers by using `findPlaceholderLayers` and `replaceLayer`, respectively.

TensorFlow-Keras Support: Import GRU layers, 2-D global max pooling layers, and PReLU advanced activation layers from TensorFlow-Keras

`importKerasNetwork` and `importKerasLayers` now support GRU layers, 2-D global max pooling layers, and PReLU advanced activation layers. For a full list of supported layers, see `importKerasNetwork` and `importKerasLayers`.

ONNX Support: Import and export networks with multiple inputs and multiple outputs

You can import an ONNX network with multiple inputs and multiple outputs. If the network has multiple inputs and a single output, use `importONNXNetwork`. If the network has multiple outputs, use `importONNXLayers`. The `importONNXLayers` function inserts placeholder layers for the outputs. After importing, you can find and replace the placeholder layers by using `findPlaceholderLayers` and `replaceLayer`, respectively. For an example, see “Import ONNX Network with Multiple Outputs”.

You can also export a trained MATLAB deep learning network that includes multiple inputs and multiple outputs to the ONNX model format by using the `exportONNXNetwork` function.

ONNX Support: Import and export networks that include exponential linear unit (ELU) layers, GRU layers, and 2-D global max pooling layers

You can now import an ONNX network that includes ELU layers, GRU layers, and 2-D global max pooling layers by using `importONNXNetwork` and `importONNXLayers`. Also, you can export a trained MATLAB deep learning network that includes these layers to the ONNX model format by using `exportONNXNetwork`. For a full list of supported layers, see `importONNXNetwork`, `importONNXLayers`, and `exportONNXNetwork`.

Pretrained Networks: Use SqueezeNet without installing support package

The `squeezenet` function no longer requires installing the Deep Learning Toolbox Model for *SqueezeNet Network* support package. To load a pretrained SqueezeNet network, use the `squeezenet` function.

Deep Learning Examples: Explore deep learning workflows

New examples to help you get started with deep learning:

- “Get Started with Deep Network Designer”
- “Get Started with Transfer Learning”
- “Interactive Transfer Learning Using SqueezeNet”
- “Transfer Learning with Deep Network Designer”
- “Create Simple Sequence Classification Network Using Deep Network Designer”
- “Visualize Image Classifications Using Maximal and Minimal Activating Images”

New examples and topics help you progress with deep learning:

- “Train Conditional Generative Adversarial Network (CGAN)”
- “Update Batch Normalization Statistics in Custom Training Loop”
- “Update Batch Normalization Statistics Using Model Function”
- “Specify Custom Layer Backward Function”
- “Specify Custom Output Layer Backward Loss Function”

New examples for experiment management tasks include:

- “Create a Deep Learning Experiment for Classification”
- “Create a Deep Learning Experiment for Regression”
- “Evaluate Deep Learning Experiments by Using Metric Functions”
- “Try Multiple Pretrained Networks for Transfer Learning”
- “Experiment with Weight Initializers for Transfer Learning”

New examples for text analytics tasks include:

- “Image Captioning Using Attention”
- “Multilabel Text Classification Using Deep Learning”

New examples for computer vision tasks include:

- “Point Cloud Classification Using PointNet Deep Learning”
- “Object Detection Using YOLO v3 Deep Learning”
- “Object Detection Using SSD Deep Learning”
- “Import Pretrained ONNX YOLO v2 Object Detector”
- “Export YOLO v2 Object Detector to ONNX”

New examples for image processing tasks include:

- “Neural Style Transfer Using Deep Learning”

New and updated examples for audio processing tasks include:

- “Train Generative Adversarial Network (GAN) for Sound Synthesis”
- “Speech Emotion Recognition”
- “Sequential Feature Selection for Audio Features”

predict Function: Improved performance for dlnetwork inference

The `predict` function for `dlnetwork` input shows improved performance for models that do not have custom layers. For example, using a GPU to process a single image using a ResNet-50 pretrained network is about 4x faster than in the previous release:

```
% Create dlnetwork and warm up
net = resnet50;
lgraph = layerGraph(net);
lgraph = removeLayers(lgraph, lgraph.Layers(end).Name);
dlnet = dlnetwork(lgraph);
dlnet = dlupdate(@gpuArray,dlnet);
x = dlarray(randn(224,224,3,'single'),'SSCB');
```

```

for i = 1:10
    predict(dlnet,x);
end

% Timing loop
wait(gpuDevice);
tic
for i = 1:100
    y = predict(dlnet,x);
end
wait(gpuDevice)
toc

```

The approximate execution times are:

R2019b: 10.4 s

R2020a: 2.6 s

The code was timed on a Windows® 10, Intel® Xeon® W-2133 @ 3.60 GHz test system with a NVIDIA® GeForce RTX 2080 Ti GPU by running the above script.

When processing batches of images, expect performance improvements of up to 4x for small batches of fixed size.

Functionality being removed or changed

rmspropupdate squared gradient decay factor default is 0.9

Behavior change

Starting in R2020a, the default value of the squared gradient decay factor in `rmspropupdate` is `0.9`. In previous versions, the default value was `0.999`. To reproduce the previous default behavior, use one of the following syntaxes:

```

[dlnet,averageSqGrad] = rmspropupdate(dlnet,grad,averageSqGrad,0.001,0.999)
[params,averageSqGrad] = rmspropupdate(params,grad,averageSqGrad,0.001,0.999)

```

sequenceInputLayer ignores padding values when normalizing

Behavior change

Starting in R2020a, `sequenceInputLayer` objects ignore padding values in the input data when normalizing. This means that the `Normalization` option in the `sequenceInputLayer` now makes training invariant to data operations, for example, `'zerocenter'` normalization now implies that the training results are invariant to the mean of the data.

If you train on padded sequences, then the calculated normalization factors may be different in earlier versions and can produce different results.

maxpool indices output argument changes shape and data type

Behavior change

Starting in R2020a, the data type and shape of the indices output argument of the `maxpool` function are changed. The `maxpool` function outputs the indices of the maximum values as a `dlarray` with the same shape and format as the pooled data, instead of a numeric vector.

The indices output of `maxpool` remains compatible with the indices input of `maxunpool`. The `maxunpool` function accepts the indices of the maximum values as a `darray` with the same shape and format as the input data. To prevent errors, use only the indices output of the `maxpool` function as the indices input to the `maxunpool` function.

To reproduce the previous behavior and obtain the indices output as a numeric vector, use the following code:

```
[dY,indx,inputSize] = maxpool(dY,poolsize);  
indx = extractdata(indx);  
indx = reshape(indx,[],1);
```

R2019b

Version: 13.0

New Features

Bug Fixes

Compatibility Considerations

Deep Learning Customization: Define and train complex networks (including GANs) using custom training loops, automatic differentiation, shared weights, and custom loss functions

In R2019b, deep learning functionality is extended to support advanced networks and workflows:

- Create and train generative adversarial networks (GANs) and other networks that require shared weights, such as Siamese networks.
- Define networks using `dlnetwork`, more than 14 deep learning functions, and more than 80 math functions that support the new deep learning data type, `dlarray`.
- Define custom loss functions and training loops.
- Write custom layers without needing to write the backward function.

To get started with customizing deep learning workflows, see:

- [Define Custom Training Loops, Loss Functions, and Networks](#)
- [Specify Training Options in Custom Training Loop](#)
- [Train Network Using Custom Training Loop](#)
- [Train Network Using Model Function](#)
- [Train Network in Parallel with Custom Training Loop](#)
- [Make Predictions Using `dlnetwork` Object](#)
- [Make Predictions Using Model Function](#)

New examples of custom deep learning workflows include:

- [Train Generative Adversarial Network \(GAN\)](#)
- [Train a Siamese Network for Dimensionality Reduction](#)
- [Train a Siamese Network to Compare Images](#)
- [Sequence-to-Sequence Classification Using 1-D Convolutions](#)
- [Sequence-to-Sequence Translation Using Attention](#)
- [Train Variational Autoencoder \(VAE\) to Generate Images](#)
- [Train Network Using Cyclical Learn Rate for Snapshot Ensembling](#)
- [Grad-CAM Reveals the Why Behind Deep Learning Decisions](#)

To learn more about automatic differentiation, see:

- [Automatic Differentiation Background](#)
- [Use Automatic Differentiation In Deep Learning Toolbox](#)

New functions are available for custom deep learning workflows.

- [List of Functions with `dlarray` Support](#)
- [Use new functions to create custom training loops.](#)

<code>dlnetwork</code>	Deep learning network for custom training loop
------------------------	--

forward	Compute deep learning network output for training
predict	Compute deep learning network output for inference
adamupdate	Update parameters using adaptive moment estimation (Adam)
sgdupdate	Update parameters using stochastic gradient descent with momentum (SGDM)
rmspropupdate	Update parameters using root mean squared propagation (RMSProp)
dlupdate	Update parameters using custom function

- Use new functions for automatic differentiation.

dlarray	Deep learning array
dlgradient	Compute gradient using automatic differentiation
dlfeval	Evaluate deep learning array function using automatic differentiation
dims	Dimension labels of dlarray
finddim	Find dimensions with specified label
stripdims	Remove dlarray labels
extractdata	Extract data from dlarray
functionToLayerGraph	Convert deep learning array function to a layer graph

- Use new functions for deep learning operations.

dlconv	Deep learning convolution
dltranspconv	Deep learning transposed convolution
lstm	Long short-term memory
fullyconnect	Sum all weighted input data and apply a bias
relu	Apply rectified linear unit activation
leakyrelu	Apply leaky rectified linear unit activation
batchnorm	Normalize each channel of input data
avgpool	Pool data to average value
maxpool	Pool data to maximum value
maxunpool	Unpool the output of a maximum pooling operation
softmax	Apply softmax activation to channel dimension
crossentropy	Categorical cross-entropy loss
sigmoid	Apply sigmoid activation
mse	Half mean squared error

Generative Adversarial Networks: Create and train generative adversarial networks (GANs) for image generation

A generative adversarial network (GAN) is a type of deep learning network that can generate data with similar characteristics as the input training data. A GAN consists of two networks that train together:

- 1 Generator — Given a vector or random values as input, this network generates data with the same structure as the training data.
- 2 Discriminator — Given batches of data containing observations from both the training data, and generated data from the generator, this network attempts to classify the observations as "real" or "generated."

The objective of the generator is to generate data that the discriminator classifies as "real." To maximize the performance of the generator, maximize the loss of the discriminator when given generated data. The objective of the discriminator is to not be "fooled" by the generator. To maximize the performance of the discriminator, minimize the loss of the discriminator when given batches of both real and generated data. These strategies result in a generator that generates convincingly realistic data and a discriminator that has learned strong feature representations that are characteristic of the training data.

To learn how to train a GAN using a custom training loop, see [Train Generative Adversarial Network \(GAN\)](#).

Siamese Networks: Create and train Siamese networks for image comparison and dimensionality reduction

Use a `dl` network with custom loss functions and training loops to create and train Siamese networks. A Siamese network consists of two or more identical subnetworks that have the same architecture and share weights and parameters. Siamese networks are useful for making comparisons. To learn more, see the following examples.

- [Train a Siamese Network to Compare Images](#)
- [Train a Siamese Network for Dimensionality Reduction](#)

Data Preprocessing: Improve training performance using different data normalization options

Data normalization can impact training, classification, and prediction accuracy. Try setting the `Normalization` option in `imageInputLayer`, `image3dInputLayer`, and `sequenceInputLayer` to different values and see which is best for your data.

New normalizations include:

- `'zscore'` — Normalize using z-score normalization.
- `'rescale-symmetric'` — Rescale the input to be in the range [-1, 1].
- `'rescale-zero-one'` — Rescale the input to be in the range [0, 1].
- `function handle` — Normalize the data using a custom function.

You can normalize using scalar statistics, or specify channel-wise or element-wise normalization using the `NormalizationDimension` option.

The software, by default, automatically calculates the required normalization statistics at training time. To save time when training, specify the required statistics for normalization and set the 'ResetInputNormalization' option in `trainingOptions` to `false`.

Visualization: Map strongly activating features of input data using occlusion

An occlusion map highlights the behavior of a network by replacing different parts of the data with an occluding mask and measuring how the spatial location of the mask affects the activations of a particular channel. Determine the parts of your input data that strongly affect activations and classification scores using the `occlusionSensitivity` function. To learn more, see [Understand Network Predictions Using Occlusion](#).

Visualization: Visualize the features learned by a DAG network using deep dream

The `deepDreamImage` function now supports DAG networks. Synthesize images that strongly activate DAG network layers using the `deepDreamImage` function. Visualizing these images highlights the features your trained network has learned, helping you understand network behavior.

Multi-Input, Multi-Output Networks: Create and train networks with multiple inputs and multiple outputs

Define and train network architectures with multiple inputs (for example, networks trained on multiple sources and types of data) or multiple outputs (for example, networks that predict both classification and regression responses). For examples showing how to train and make predictions with a network with multiple predictions, see:

- [Train Network with Multiple Outputs](#)
- [Assemble Multiple-Output Network for Prediction](#)
- [Make Predictions Using Model Function](#)

For more information, see [Multiple-Input and Multiple-Output Networks](#).

Long Short-Term Memory Networks: Pad or truncate sequences on the left

The location of the padding and truncation can impact training, classification, and prediction accuracy. Try setting the 'SequencePaddingDirection' option in `trainingOptions` to 'left' or 'right' and see which is best for your data.

Because LSTM layers process sequence data one time step at a time, when the layer `OutputMode` property is 'last', any padding in the final time steps can negatively influence the layer output. To pad or truncate sequence data on the left, set the 'SequencePaddingDirection' option to 'left'.

For sequence-to-sequence networks (when the `OutputMode` property is 'sequence' for each LSTM layer), any padding in the first time steps can negatively influence the predictions for the earlier time steps. To pad or truncate sequence data on the right, set the 'SequencePaddingDirection' option to 'right'.

To learn more about the effect of padding, truncating, and splitting the input sequences, see [Sequence Padding, Truncation, and Splitting](#).

Long Short-Term Memory Networks: Compute intermediate layer activations

The `activations` function now supports LSTM networks. Investigate and visualize the features learned by LSTM networks from sequence and time series data by extracting the activations using the `activations` function. To learn more, see [Visualize Activations of LSTM Network](#).

ONNX Support: Export networks that combine CNN and LSTM layers and networks that include 3-D CNN layers to ONNX format

You can now export deep networks that combine convolutional neural networks (CNNs) and long short-term memory (LSTM) layers to ONNX format. `exportONNXNetwork` now also supports 3-D CNN layers. For a full list of supported layers, see `exportONNXNetwork`.

Global Average Pooling: Reduce network size and help prevent overfitting using global average pooling layers

A global average pooling layer performs downsampling by computing the mean of the spatial dimensions of the input. For 2-D data, create a global average pooling layer with the `globalAveragePooling2dLayer` function. For 3-D data, use the `globalAveragePooling3dLayer` function.

Cropping: Crop 2-D and 3-D input data to size of reference feature map

Crop 2-D and 3-D input data to the size of a reference feature map using `crop2dLayer` and `crop3dLayer` objects, respectively.

Starting in R2019b, you can use `crop2dLayer` objects in Deep Learning Toolbox without Computer Vision Toolbox™. In previous versions, this object required Computer Vision Toolbox.

Deep Learning Examples: Explore deep learning workflows

New examples and topics help you progress with deep learning:

- [Preprocess Data for Domain-Specific Deep Learning Applications](#)
- [Chemical Process Fault Detection Using Deep Learning](#)
- [View Network Behavior Using tsne](#)

New examples for computer vision tasks include:

- [Getting Started with Object Detection Using Deep Learning \(Computer Vision Toolbox\)](#)
- [Augment Bounding Boxes for Object Detection](#)
- [Augment Pixel Labels for Semantic Segmentation](#)

New examples for image processing tasks include:

-
- Augment Images for Deep Learning Workflows Using Image Processing Toolbox
 - Deep Learning Classification of Large Multiresolution Images

New examples for signal and audio processing tasks include:

- Label QRS Complexes and R Peaks of ECG Signals Using Deep Network
- Pedestrian and Bicyclist Classification Using Deep Learning
- Radar Waveform Classification Using Deep Learning
- Sequential Feature Selection for Speech Emotion Recognition
- Keyword Spotting in Noise Using MFCC and LSTM Networks
- Acoustic Scene Recognition Using Late Fusion

New examples for reinforcement learning tasks include:

- Create Simulink Environment and Train Agent
- Create Agent Using Deep Network Designer and Train Using Image Observations
- Train DDPG Agent to Swing Up and Balance Pendulum with Image Observation
- Train DQN Agent for Lane Keeping Assist Using Parallel Computing

New code generation examples include:

- Generate C++ Code for Object Detection Using YOLO v2 and Intel MKL-DNN
- Code Generation and Deployment of MobileNet-v2 Network to Raspberry Pi
- Deep Learning Prediction on ARM Mali GPU
- Code Generation for a Sequence-to-Sequence LSTM Network

Functionality being removed or changed

AverageImage property of imageInputLayer and image3dInputLayer will be removed

Still runs

The AverageImage property of imageInputLayer and image3dInputLayer will be removed. Use Mean instead. To update your code, replace all instances of AverageImage with Mean. There are no differences between the properties that require additional updates to your code.

imageInputLayer and image3dInputLayer, by default, use channel-wise normalization

Behavior change

Starting in R2019b, imageInputLayer and image3dInputLayer, use channel-wise normalization by default. In previous versions, these layers used element-wise normalization. To reproduce this behavior, set the NormalizationDimension option of these layers to 'element'.

sequenceInputLayer, by default, uses channel-wise zero-center normalization

Behavior change

Starting in R2019b, sequenceInputLayer uses channel-wise zero-center normalization by default when Normalization is 'zero-center'. In previous versions, this layer used element-wise normalization. To reproduce this behavior, set the NormalizationDimension option of this layer to 'element'.

R2019a

Version: 12.1

New Features

Bug Fixes

Compatibility Considerations

Deep Network Designer: Create networks for computer vision and text applications

Use **Deep Network Designer** to create networks for computer vision and text applications. Deep Network Designer now supports deep learning layers in Computer Vision Toolbox and Text Analytics Toolbox for applications such as semantic segmentation, object detection, and text classification. For a list of layers, see List of Deep Learning Layers.

Deep Network Designer: Generate MATLAB code that recreates your network

Generate MATLAB code that recreates a network constructed in Deep Network Designer and returns it as a `layerGraph` object or a `Layer` array in the MATLAB workspace. Use the generated code to modify the network using the command line and automate deep learning workflows. You can also save any pretrained weights and use the generated code to recreate the network including weights.

For more information, see [Generate MATLAB Code from Deep Network Designer](#).

Convolutions for Image Sequences: Create LSTM networks for video classification and gesture recognition

Create deep learning networks for data containing sequences of images such as video data and medical images.

- To input sequences of images into a network, use `sequenceInputLayer`.
- To apply convolutional operations independently on each time step, first convert the sequences of images to an array of images using a `sequenceFoldingLayer`.
- To restore the sequence structure after applying these operations, use a `sequenceUnfoldingLayer`.
- To convert the output to an array of feature vectors, use a `flattenLayer`. After the flatten layer, you can use LSTM and BiLSTM layers.

For an example, see [Classify Videos Using Deep Learning](#).

Layer Initialization: Initialize layer weights and biases using initializers or a custom function

Initialize layer weights and biases using initializers such as the Glorot initializer (also known as the Xavier initializer), the He initializer, and orthogonal initializers. To specify the initializer for the weights and biases of convolutional layers or fully connected layers, use the `'WeightsInitializer'` and `'BiasInitializer'` name-value pairs of the layers, respectively. To specify the initializer for the input weights, the recurrent weights, and the biases for LSTM and BiLSTM layers, use the `'InputWeightsInitializer'`, `'RecurrentWeightsInitializer'`, and `'BiasInitializer'` name-value pairs, respectively.

You can specify initializers for these layers:

- `batchNormalizationLayer`
- `biLstmLayer`

-
- `convolution2dLayer`
 - `convolution3dLayer`
 - `fullyConnectedLayer`
 - `groupedConvolution2dLayer`
 - `lstmLayer`
 - `transposedConv2dLayer`
 - `transposedConv3dLayer`
 - `wordEmbeddingLayer` (Text Analytics Toolbox)

For an example showing how to compare the different initializers, see [Compare Layer Weight Initializers](#). For an example showing how to create a custom initialization function, see [Specify Custom Weight Initialization Function](#).

Grouped Convolutions: Create efficient deep learning networks with grouped and channel-wise convolutions

When training convolutional neural networks from scratch, for some networks, you can speed up training and prediction by replacing standard convolutions with grouped or channel-wise (also known as depth-wise) convolutions. To create a grouped convolutional layer, use `groupedConvolution2dLayer`. For channel-wise convolution, use `groupedConvolution2dLayer` and set `NumGroups` to `'channel-wise'`.

For an example showing how to create a block of layers for channel-wise separable convolution (also known as depth-wise separable convolution), see [Create Layers for Channel-Wise Separable Convolution](#).

3-D Support: New layers enable deep learning with 3-D data

These new layers enable you to work with 3-D data:

- `image3dInputLayer`
- `convolution3dLayer`
- `transposedConv3dLayer`
- `averagePooling3dLayer`
- `maxPooling3dLayer`
- `concatenationLayer`

These existing layers are enhanced to support 3-D data in deep learning networks:

- `reluLayer`
- `leakyReluLayer`
- `clippedReluLayer`
- `fullyConnectedLayer`
- `softmaxLayer`
- `classificationLayer`
- `regressionLayer`

For a list of available layers, see [List of Deep Learning Layers](#). For an example showing how to train a network using 3-D data, see [3-D Brain Tumor Segmentation Using Deep Learning](#).

Custom Layers: Create custom layers with multiple inputs or multiple outputs

You can now define custom layers with multiple inputs or multiple outputs. If Deep Learning Toolbox does not provide the deep learning layer you need for your task, then you can define your own layer by specifying the layer forward and backward functions.

For more information about defining custom layers, see [Define Custom Deep Learning Layers](#). To learn how to check that the layer is valid automatically using the `checkLayer` function, see [Check Custom Layer Validity](#).

Deep Learning Acceleration: Optimize deep learning applications using MEX functions

Accelerate prediction, classification, and feature extraction using automatically generated MEX functions. Use the 'Acceleration', 'mex' name-value pair with the following functions.

- `activations`
- `classify`
- `predict`

Pretrained Networks: Perform transfer learning with NASNet-Large, NASNet-Mobile, MobileNet-v2, ShuffleNet, Xception, and Places365-GoogLeNet pretrained convolutional neural networks

You can now install add-ons for the NASNet-Large, NASNet-Mobile, MobileNet-v2, ShuffleNet, Xception, and Places365-GoogLeNet pretrained convolutional neural networks. To download and install the pretrained networks, use the Add-On Explorer. You can also download the networks from MathWorks Deep Learning Toolbox Team. After you install the add-ons, use the `nasnetlarge`, `nasnetmobile`, `mobilenetv2`, `shufflenet`, `xception`, and `googlenet` functions to load the networks, respectively. Places365-GoogLeNet is a version of GoogLeNet that is trained on the Places365 data set and classifies images into 365 different place categories, such as field, park, runway, and lobby. To load this network, use `net = googlenet('Weights','places365')`.

To retrain a network on a new classification task, follow the steps in [Train Deep Learning Network to Classify New Images](#) and load the pretrained network you want to use instead of GoogLeNet.

For more information on pretrained neural networks in MATLAB, see [Pretrained Deep Neural Networks](#).

Deep Learning Layers: Hyperbolic tangent and exponential linear unit activation layers

You can now use hyperbolic tangent (`tanh`) and exponential linear unit (ELU) layers as activation layers in deep learning networks. To create a `tanh` or ELU layer, use `tanhLayer` and `eluLayer`, respectively.

For a list of available layers, see List of Deep Learning Layers.

Deep Learning Visualization: Investigate network predictions using class activation mapping

Follow the example Investigate Network Predictions Using Class Activation Mapping and use the class activation mapping (CAM) technique to investigate and explain the predictions of a deep convolutional neural network for image classification.

Deep Learning Examples: Explore deep learning workflows

New examples and topics help you progress with deep learning:

- Investigate Network Predictions Using Class Activation Mapping
- Classify Videos Using Deep Learning
- Run Multiple Deep Learning Experiments
- Train Network Using Out-of-Memory Sequence Data
- Compare Layer Weight Initializers
- Specify Custom Weight Initialization Function

New examples for computer vision problems include:

- Object Detection Using YOLO v2 Deep Learning
- 3-D Brain Tumor Segmentation Using Deep Learning

New examples for text problems include:

- Classify Text Data Using Convolutional Neural Network
- Classify Out-of-Memory Text Data Using Deep Learning

New examples for signal and audio processing include:

- Cocktail Party Source Separation Using Deep Learning Networks
- Voice Activity Detection in Noise Using Deep Learning
- Modulation Classification with Deep Learning
- Spoken Digit Recognition with Wavelet Scattering and Deep Learning
- Waveform Segmentation Using Deep Learning

New code generation examples include:

- Code Generation for Semantic Segmentation Network using U-net
- Train and Deploy Fully Convolutional Networks for Semantic Segmentation
- Code Generation for Object Detection Using YOLO v2
- Code Generation for Deep Learning on ARM Targets
- Code Generation for Deep Learning on Raspberry Pi
- Deep Learning Prediction with ARM Compute Using cnncodegen

Functionality being removed or changed

Glorot is default weights initialization for convolution, transposed convolution, and fully connected layers

Behavior change

Starting in R2019a, the software, by default, initializes the layer weights of `convolution2dLayer`, `transposedConv2dLayer`, and `fullyConnectedLayer` using the Glorot initializer. This behavior helps stabilize training and usually reduces the training time of deep networks.

In previous releases, the software, by default, initializes the layer weights by sampling from a normal distribution with a mean of zero and a variance of 0.01. To reproduce this behavior, set the `'WeightsInitializer'` option of these layers to `'narrow-normal'`.

Glorot is default input weights initialization for LSTM and BiLSTM layers

Behavior change

Starting in R2019a, the software, by default, initializes the layer input weights of `lstmLayer` and `biLstmLayer` using the Glorot initializer. This behavior helps stabilize training and usually reduces the training time of deep networks.

In previous releases, the software, by default, initializes the layer input weights by sampling from a normal distribution a mean of zero and a variance of 0.01. To reproduce this behavior, set the `'InputWeightsInitializer'` option of these layers to `'narrow-normal'`.

Orthogonal is default recurrent weights initialization for LSTM and BiLSTM layers

Behavior change

Starting in R2019a, the software, by default, initializes the layer recurrent weights of LSTM and BiLSTM layers with Q , the orthogonal matrix given by the QR decomposition of $Z = QR$ for a random matrix Z sampled from a unit normal distribution. This behavior helps stabilize training and usually reduces the training time of deep networks.

In previous releases, the software, by default, initializes the layer recurrent weights by sampling from a normal distribution with a mean of zero and a variance of 0.01. To reproduce this behavior, set the `'RecurrentWeightsInitializer'` option of the layer to `'narrow-normal'`.

Custom layers have new properties NumInputs, InputNames, NumOutputs, and OutputNames

Starting in R2019a, custom layers have the new properties `NumInputs`, `InputNames`, `NumOutputs`, and `OutputNames`. These properties enable support for custom layers with multiple inputs and multiple outputs.

If you use a custom layer created in R2018b or earlier, the layer cannot have any properties named `NumInputs`, `InputNames`, `NumOutputs`, or `OutputNames`. You must rename these properties to use the layer in R2019a and onwards.

Cropping property of TransposedConvolution2DLayer will be removed

Still runs

Cropping property of `TransposedConvolution2DLayer` will be removed. Use `CroppingSize` instead. To update your code, replace all instances of the `Cropping` property with `CroppingSize`.

matlab.io.datastore.MiniBatchable is not recommended for custom image preprocessing

Still runs

Before R2018a, to perform custom image preprocessing for training deep learning networks, you had to specify a custom read function using the `readFcn` property of `imageDatastore`. However, reading files using a custom read function was slow because `imageDatastore` did not prefetch files.

In R2018a, the four classes `matlab.io.datastore.MiniBatchable`, `matlab.io.datastore.BackgroundDispatchable`, `matlab.io.datastore.Shuffleable`, and `matlab.io.datastore.PartitionableByIndex` were introduced as a solution to perform custom image preprocessing with support for prefetching, shuffling, and parallel training. Implementing a custom mini-batch datastore using these classes has several challenges and limitations.

- In addition to specifying the preprocessing operations, you must also define properties and methods to support reading data in batches, reading data by index, and partitioning and shuffling data.
- You must specify a value for the `NumObservations` property, but this value may be ill-defined or difficult to define in real-world applications.
- Custom mini-batch datastores are not flexible enough to support common deep learning workflows, such as deployed workflows using GPU Coder™.

Starting in R2019a, built-in datastores natively support prefetch, shuffling, and parallel training when reading batches of data. The `transform` function is the preferred way to perform custom image preprocessing using built-in datastores. The `combine` function is the preferred way to concatenate read data from multiple datastores, including transformed datastores. Concatenated data can serve as the network inputs and expected responses for training deep learning networks. The `transform` and `combine` functions have several advantages over custom mini-batch datastores.

- The functions enable data preprocessing and concatenation for all types of datastores, including `imageDatastore`.
- The `transform` function requires you to define only the data processing pipeline.
- When used on a deterministic datastore, the functions support `all` data types and MapReduce.
- The functions support deployed workflows.

For more information about custom image preprocessing, see [Preprocess Images for Deep Learning](#).

matlab.io.datastore.BackgroundDispatchable and matlab.io.datastore.PartitionableByIndex are not recommended

Still runs

`matlab.io.datastore.BackgroundDispatchable` and `matlab.io.datastore.PartitionableByIndex` add support for prefetching and parallel training to custom mini-batch datastores. You can use custom mini-batch datastores to preprocess sequence, time series, or text data, but recurrent networks such as LSTM networks do not support prefetching or parallel and multi-GPU training.

Starting in R2019a, built-in datastores natively support prefetching and parallel training, so custom mini-batch datastores are not recommended for custom image preprocessing.

There are no plans to remove `matlab.io.datastore.BackgroundDispatchable` or `matlab.io.datastore.PartitionableByIndex` at this time.

R2018b

Version: 12.0

New Features

Bug Fixes

Compatibility Considerations


Renamed Product: Neural Network Toolbox renamed to Deep Learning Toolbox

Neural Network Toolbox™ now has the name Deep Learning Toolbox.

Deep Network Designer: Edit and build deep learning networks

Build, visualize, and edit deep learning networks interactively in the **Deep Network Designer** app.

- Import pretrained networks and edit them for transfer learning.
- Edit networks and build new networks from scratch.
- Drag and drop to add new layers and create new connections.
- View and edit layer properties.
- Analyze the network to check for correct architecture and detect problems before training.
- Export the network to the workspace, where you can save or train the network.



For examples, see:

- Transfer Learning with Deep Network Designer
- Build Networks with Deep Network Designer
- Interactive Transfer Learning Using AlexNet

ONNX Support: Import and export models using the ONNX model format for interoperability with other deep learning frameworks

Export a trained MATLAB deep learning network to the ONNX™ (Open Neural Network Exchange) model format using the `exportONNXNetwork` function. You can then import the ONNX model to other deep learning frameworks, such as TensorFlow™, that support ONNX model import.

Import deep learning networks and network architectures from ONNX using `importONNXNetwork` and `importONNXLayers`.

Network Analyzer: Visualize, analyze, and find problems in network architectures before training

Analyze deep learning network architectures using the `analyzeNetwork` function. Use the network analyzer to visualize and understand the network architecture, check that you have defined the architecture correctly, and detect problems before training. Problems that `analyzeNetwork` detects include missing or disconnected layers, incorrectly sized layer inputs, an incorrect number of layer inputs, and invalid graph structures. For more information, see `analyzeNetwork`.

LSTM Network Validation: Validate networks for time series data automatically during training

Validate LSTM networks at regular intervals during network training, and automatically stop training when validation metrics stop improving.

To perform network validation during training, specify validation data using the 'ValidationData' name-value pair argument of `trainingOptions`. You can change the validation frequency using the 'ValidationFrequency' name-value pair argument. For more information, see `Specify Validation Data`.

For an example showing how to specify validation data for an LSTM network, see `Classify Text Data Using Deep Learning`.

Network Assembly: Assemble networks from imported layers and weights without training

Assemble networks from imported layers and weights without training using the `assembleNetwork` function. You can use this function for the following tasks:

- Convert a layer array or layer graph to a network ready for prediction.
- Assemble networks from imported layers.
- Modify the weights of a trained network.

For an example showing how to assemble a network from pretrained layers, see `Assemble Network from Pretrained Keras Layers`.

Output Layer Validation: Verify custom output layers for validity, GPU compatibility, and correctly defined gradients

Check custom output layers for validity using `checkLayer`. You can check GPU compatibility and correctly defined gradients. For more information, see [Check Custom Layer Validity](#).

Visualization: Investigate network predictions using confusion matrix charts

Use `confusionchart` to calculate and plot a confusion matrix for a classification problem using true and predicted labels. A confusion matrix helps you evaluate how well the classifier performs on a data set and identify where it is accurate or inaccurate. Additionally, you can:

- Create a confusion matrix chart from a nonnegative integer-valued confusion matrix.
- Control the appearance and behavior of the confusion matrix chart by modifying `ConfusionMatrixChart` Properties.
- View summary statistics about your data, such as the number of correctly and incorrectly classified observations for each predicted and true class.
- Sort the classes of the confusion matrix by the total number of correctly classified observations, the class-wise precision (positive predictive value), or the class-wise recall (true positive rate) by using `sortClasses`.

Dilated Convolution: Change the dilation factor of convolutional layers to enhance prediction accuracy for tasks such as semantic segmentation

Specify dilated convolutions (also known as atrous convolutions) using the `DilationFactor` property of `convolution2dLayer`. Use dilated convolutions to increase the receptive field (the area of the input that the layer can see) of the layer without increasing the number of parameters or computation.

For an example showing how to use dilated convolutions for semantic segmentation, see [Semantic Segmentation Using Dilated Convolutions](#)

Sequence Mini-Batch Datastores: Develop datastores for sequence, time series, and signal data

Use custom mini-batch datastores for sequence, time series, and signal data when data is too large to fit in memory, or to perform specific operations when reading batches of data. You can optionally add support for functionalities such as shuffling during training, parallel and multi-GPU training, and background dispatch. For more information, see [Develop Custom Mini-Batch Datastore](#).

For an example showing how to use a custom mini-batch datastore for sequence data, see [Train Network Using Out-of-Memory Sequence Data](#).

Pretrained Networks: Perform transfer learning with ResNet-18 and DenseNet-201 pretrained convolutional neural networks

You can now install add-ons for the ResNet-18 and DenseNet-201 pretrained convolutional neural networks. To download and install the pretrained networks, use the Add-On Explorer. You can also

download the networks from MathWorks Deep Learning Toolbox Team. After you install the add-ons, use the `resnet18` and `densenet201` functions to load the networks, respectively.

To retrain a network on a new classification task, follow the steps of Train Deep Learning Network to Classify New Images and load ResNet-18 or DenseNet-201 instead of GoogLeNet.

For more information on pretrained neural networks in MATLAB, see Pretrained Convolutional Neural Networks.

TensorFlow-Keras: Import LSTM and BiLSTM layers from TensorFlow-Keras

Import pretrained LSTM and BiLSTM networks and layers from TensorFlow-Keras by using the `importKerasNetwork` and `importKerasLayers` functions.

To use `importKerasNetwork` and `importKerasLayers`, you must install the Deep Learning Toolbox Importer for TensorFlow-Keras Models support package. If this support package is not installed, the functions provide a download link.

Caffe Importer: Import directed acyclic graph networks from Caffe

Import directed acyclic graph (DAG) networks and network architectures from Caffe. In previous releases, you could only import networks with layers arranged in a sequence. To import a Caffe network with weights, use `importCaffeNetwork`. To import a network architecture without weights, use `importCaffeLayers`.

LSTM Layer Activation Functions: Specify state and gate activation functions

For LSTM layers, specify state and gate activation functions using the `StateActivationFunction` and `GateActivationFunction` properties of `lstmLayer` respectively. For BiLSTM layers, specify the state and gate activation functions using the `StateActivationFunction` and `GateActivationFunction` properties of `bilstmLayer`, respectively.

Deep Learning: New network layers

You can now use the following layers in deep learning networks:

- `wordEmbeddingLayer`
- `roiInputLayer`
- `roiMaxPooling2dLayer`
- `regionProposalLayer`
- `rpnSoftmaxLayer`
- `rpnClassificationLayer`
- `rcnnBoxRegressionLayer`
- `weightedClassificationLayer` (custom layer example)
- `dicePixelClassificationLayer` (custom layer example)

For a list of available layers, see [List of Deep Learning Layers](#).

Image Data Augmenter: Additional options for augmenting and visualizing images

The `imageDataAugmenter` object now offers more flexibility for transforming images and visualizing the effect of the transformation.

- The `augment` function can apply identical random transformations to multiple images. Use the `augment` function to apply identical transformations to input and response image pairs in a custom mini-batch datastore.

You can also use the `augment` function to easily visualize the transformations applied to sample images.

- The new `'RandScale'` property of `imageDataAugmenter` scales an image uniformly in the vertical and horizontal directions to maintain the image aspect ratio.
- Several properties of `imageDataAugmenter` now support sampling over disjoint intervals or using nonuniform probability distributions. Specify a custom sampling function using a function handle.

Deep Learning Examples: Explore deep learning workflows

New examples and topics help you progress with deep learning.

- [Use the example Train Deep Learning Network to Classify New Images to fine-tune any pretrained network for a new image classification task.](#)
- [Compare Pretrained Networks](#)
- [Transfer Learning with Deep Network Designer](#)
- [Interactive Transfer Learning Using AlexNet](#)
- [Build Networks with Deep Network Designer](#)
- [Deep Learning Tips and Tricks](#)
- [Assemble Network from Pretrained Keras Layers](#)
- [List of Deep Learning Layers](#)
- [Convert Classification Network into Regression Network](#)
- [Resume Training from Checkpoint Network](#)
- [Semantic Segmentation Using Dilated Convolutions](#)
- [Image Processing Operator Approximation Using Deep Learning](#)
- [Assemble Network from Pretrained Keras Layers](#)
- [Train Network Using Out-of-Memory Sequence Data](#)
- [Denoise Speech Using Deep Learning Networks](#)
- [Classify Gender Using Long Short-Term Memory Networks](#)

New examples for text problems include:

- [Classify Text Data Using Deep Learning](#)
- [Generate Text Using Deep Learning](#)

-
- Pride and Prejudice and MATLAB
 - Word-By-Word Text Generation Using Deep Learning
 - Classify Out-of-Memory Text Data Using Custom Mini-Batch Datastore

New examples for deep learning code generation include:

- Deep Learning Prediction with Intel MKL-DNN
- Code Generation for Denoising Deep Neural Network
- Code Generation for Semantic Segmentation Network

Functionality being removed or changed

'ValidationPatience' training option default is Inf

Behavior change

Starting in R2018b, the default value of the 'ValidationPatience' option in `trainingOptions` is `Inf`, which means that automatic stopping via validation is turned off. This behavior prevents the training from stopping before sufficiently learning from the data.

In previous releases, the default value is 5. To reproduce this behavior, set the 'ValidationPatience' option in `trainingOptions` to 5.

ClassNames property of ClassificationOutputLayer will be removed

Still runs

`ClassNames` property of `ClassificationOutputLayer` will be removed. Use `Classes` instead. To update your code, replace all instances of the `ClassNames` property with `Classes`. There are some differences between the functions that require additional updates to your code.

The `ClassNames` property contains a cell array of character vectors. The `Classes` property contains a categorical array. To use the `Classes` property with functions that require cell array input, convert the classes using the `cellstr` function.

'ClassNames' option of importKerasNetwork, importCaffeNetwork, and importONNXNetwork will be removed

Still runs

The 'ClassNames' option of `importKerasNetwork`, `importCaffeNetwork`, and `importONNXNetwork` will be removed. Use 'Classes' instead. To update your code, replace all instances of 'ClassNames' with 'Classes'. There are some differences between the corresponding properties in classification output layers that require additional updates to your code.

The `ClassNames` property of a classification output layer is a cell array of character vectors. The `Classes` property is a categorical array. To use the value of `Classes` with functions that require cell array input, convert the classes using the `cellstr` function.

Different file name for checkpoint networks

Behavior change

Starting in R2018b, when saving checkpoint networks, the software assigns file names beginning with `net_checkpoint_`. In previous releases, the software assigns file names beginning with `convnet_checkpoint_`. For more information, see the 'CheckpointPath' option in `trainingOptions`.

If you have code that saves and loads checkpoint networks, then update your code to load files with the new name.

R2018a

Version: 11.1

New Features

Bug Fixes

Compatibility Considerations

Long Short-Term Memory (LSTM) Networks: Solve regression problems with LSTM networks and learn from full sequence context using bidirectional LSTM layers

Use recurrent LSTM networks to solve regression problems and use bidirectional LSTM networks to learn from full sequence context.

For an example showing how to create an LSTM network for sequence-to-sequence regression, see [Sequence-to-Sequence Regression Using Deep Learning](#). For an example showing how to forecast future values in a time series, see [Time Series Forecasting Using Deep Learning](#).

To create an LSTM network that learns from complete sequences at each time step, include a bidirectional LSTM layer in your network by using `biLstmLayer`.

Deep Learning Optimization: Improve network training using Adam, RMSProp, and gradient clipping

Use the Adam (adaptive moment estimation) and RMSProp (root-mean-square propagation) optimizers and gradient clipping to train deep learning neural networks.

To create training options for the Adam or RMSProp solvers, use the `trainingOptions` function. `trainingOptions('adam')` and `trainingOptions('rmsprop')` create training options for the Adam and RMSProp solvers, respectively. To specify solver options, use the `'GradientDecayFactor'`, `'SquaredGradientDecayFactor'`, and `'Epsilon'` name-value pair arguments.

To use gradient clipping when training neural networks, use the `'GradientThreshold'` and `'GradientThresholdMethod'` name-value pair arguments of `trainingOptions`.

Deep Learning Data Preprocessing: Read data and define preprocessing operations efficiently for training and prediction

Read and preprocess data efficiently for neural network training, prediction, and validation. You can use a built-in type of mini-batch datastore, such as an `augmentedImageDatastore`, to perform data augmentation with limited preprocessing operations, including resizing, rotation, reflection, and cropping.

Define custom data preprocessing operations by creating your own mini-batch datastore. You can optionally add support for functionality such as shuffling during training, parallel and multi-GPU training, and background dispatch. For more information, see [Develop Custom Mini-Batch Datastore](#).

Compatibility Considerations

In previous releases, you could preprocess images with resizing, rotation, reflection, and other geometric transformations by using an `augmentedImageSource`. The `augmentedImageSource` function now creates an `augmentedImageDatastore` object. An `augmentedImageDatastore` behaves similarly to an `augmentedImageSource`, with additional properties and methods to assist with data augmentation.

You can now use `augmentedImageDatastore` for both training and prediction. In the previous release, you could use `augmentedImageSource` for training but not prediction.

Deep Learning Layer Validation: Check layers for validity, GPU compatibility, and correctly defined gradients

If you create a custom deep learning layer, then you can check that your layer is valid and GPU compatible, and that it calculates gradients correctly, by using `checkLayer`.

Directed Acyclic Graph (DAG) Networks: Accelerate DAG network training using multiple GPUs and compute intermediate layer activations

Speed up training of deep learning DAG networks using multiple GPUs. To train networks using multiple GPUs, specify the 'ExecutionEnvironment' name-value pair argument of `trainingOptions`.

To use DAG networks for feature extraction or visualization of layer activations, use the `activations` function.

Confusion Matrix: Plot confusion matrices for categorical labels

Plot confusion matrices for categorical labels by using the `plotconfusion` function. `plotconfusion(targets, outputs)` plots a confusion matrix for the true labels `targets` and the predicted labels `outputs`. For an example, see [Plot Confusion Matrix Using Categorical Labels](#).

Multispectral Deep Learning: Train convolutional neural networks on multispectral images

Train convolutional neural networks on images with an arbitrary number of channels. To specify the number of input channels to a network, set the `InputSize` property of the image input layer. For an example, see [Semantic Segmentation of Multispectral Images Using Deep Learning](#).

Directed Acyclic Graph (DAG) Network Editing: Replace a layer in a layer graph more easily

Easily replace a layer in a `LayerGraph` object with a new layer or array of layers by using the `replaceLayer` function. In previous releases, you could replace layers by editing the layer graph, but you had to update the layer connections manually. The new function updates the layer connections automatically.

The `replaceLayer` function requires the *Neural Network Toolbox Importer for TensorFlow-Keras Models* support package. If this support package is not installed, type `importKerasLayer` or `importKerasNetwork` in the command line for a download link.

Pretrained Networks: Accelerate transfer learning by freezing layer weights

Speed up training of pretrained convolutional neural networks by freezing the weights of initial network layers. Freeze the layer weights by setting the learning rate factors of the layers to zero. If

you freeze the weights of the initial layers of a network, then `trainNetwork` does not compute the gradients of the frozen layer weights. For an example showing how to freeze layer weights, see [Transfer Learning Using GoogLeNet](#).

Pretrained Networks: Transfer learning with pretrained SqueezeNet and Inception-ResNet-v2 convolutional neural networks

You can now install add-ons for the SqueezeNet and Inception-ResNet-v2 pretrained convolutional neural networks. To download and install the pretrained networks, use the Add-On Explorer. You can also download the networks from MathWorks Neural Network Toolbox Team. After you install the add-ons, use the `squeezenet` and `inceptionresnetv2` functions to load the networks, respectively.

To retrain a network on a new classification task, follow the steps of [Transfer Learning Using GoogLeNet](#). Load a SqueezeNet or Inception-ResNet-v2 network instead of GoogLeNet, and change the names of the layers that you remove and connect to match the names of your pretrained network. For more information, see `squeezenet` and `inceptionresnetv2`.

For more information on pretrained neural networks in MATLAB, see [Pretrained Convolutional Neural Networks](#).

Deep Learning Network Analyzer: Visualize, analyze, and find issues in network architectures

Analyze deep learning network architectures using the `analyzeNetwork` function. Use the network analyzer to visualize and understand the network architecture, check that you have defined the architecture correctly, and detect problems before training. Problems that `analyzeNetwork` detects include missing or disconnected layers, mismatching or incorrect sizes of layer inputs, incorrect number of layer inputs, and invalid graph structures.

The `analyzeNetwork` function requires the Deep Learning Network Analyzer for Neural Network Toolbox support package. To download and install support package, use the Add-On Explorer. You can also download the support package from MathWorks Neural Network Toolbox Team. For more information, see `analyzeNetwork`.

ONNX Support: Import and export models using the ONNX model format for interoperability with other deep learning frameworks

Export a trained MATLAB deep learning network to the ONNX (Open Neural Network Exchange) model format using the `exportONNXNetwork` function. You can then import the ONNX model to other deep learning frameworks, such as TensorFlow, that support ONNX model import.

Import deep learning networks and network architectures from ONNX using `importONNXNetwork` and `importONNXLayers`.

Deep Learning Speech Recognition: Train a simple deep learning model to detect speech commands

Use the Deep Learning Speech Recognition example to learn how to train a simple neural network to recognize a given set of speech commands (Requires Audio Toolbox™).

Parallel Deep Learning Workflows: Explore deep learning with multiple GPUs locally or in the cloud

Use new examples to explore options for scaling up deep learning training. You can use multiple GPUs locally or in the cloud without changing your code. Use parallel computing to train multiple networks locally or on cloud clusters, and use datastores to access cloud data. New examples include:

- Train Network in the Cloud Using Built-in Parallel Support
- Use `parfor` to Train Multiple Deep Learning Networks
- Use `parfeval` to Train Multiple Deep Learning Networks
- Upload Deep Learning Data to the Cloud
- Send Deep Learning Batch Job To Cluster

To learn about options, see [Scale Up Deep Learning in Parallel and in the Cloud](#).

Deep Learning Examples: Explore deep learning applications

Use examples to learn about different applications of deep learning. New examples for sequence, time series, text, and image problems include:

- Deep Learning Speech Recognition
- Train Residual Network on CIFAR-10
- Time Series Forecasting Using Deep Learning
- Sequence-to-Sequence Classification Using Deep Learning
- Sequence-to-Sequence Regression Using Deep Learning
- Classify Text Data Using Deep Learning
- Semantic Segmentation of Multispectral Images Using Deep Learning
- Single Image Super-Resolution Using Deep Learning
- JPEG Image Deblocking Using Deep Learning
- Remove Noise from Color Image Using Pretrained Neural Network

For more examples of deep learning applications, see [Deep Learning Applications](#) and [Deep Learning GPU Code Generation](#).

Functionality Being Removed or Changed

Functionality	Result	Use Instead	Compatibility Considerations
Default output format of activations	Still runs	Not applicable	In R2018a, the new default output format of activations is a 4-D array. To reproduce the old default behavior, set the 'OutputAs' value to 'rows'.

Functionality	Result	Use Instead	Compatibility Considerations
augmentedImageSource	Still runs	augmentedImageDatastore	In R2018a, you cannot create an augmentedImageSource object. The augmentedImageSource function now creates an augmentedImageDatastore object.
OutputSize property of lstmLayer	Still runs	NumHiddenUnits property	Replace all instances of the OutputSize property of lstmLayer objects with NumHiddenUnits.

R2017b

Version: 11.0

New Features

Bug Fixes

Compatibility Considerations

Directed Acyclic Graph (DAG) Networks: Create deep learning networks with more complex architecture to improve accuracy and use many popular pretrained models

You can create and train DAG networks for deep learning. A DAG network is a neural network whose layers can be arranged as a directed acyclic graph. DAG networks can have a more complex architecture with layers that have inputs from, or outputs to, multiple layers.

To create and train a DAG network:

- Create a `LayerGraph` object using `layerGraph`. The layer graph specifies the network architecture. You can create an empty layer graph and then add layers to it. You can also create a layer graph directly from an array of network layers. The layers in the graph are automatically connected sequentially.
- Add layers to the layer graph using `addLayers` and remove layers from the graph using `removeLayers`.
- Connect layers of the layer graph using `connectLayers` and disconnect layers using `disconnectLayers`.
- Plot the network architecture using `plot`.
- Train the network using the layer graph as the layers input argument to `trainNetwork`. The trained network is a `DAGNetwork` object.
- Perform classification and prediction on new data using `classify` and `predict`.

For an example showing how to create and train a DAG network, see [Create and Train DAG Network for Deep Learning](#).

You can also load a pretrained DAG network by installing the *Neural Network Toolbox Model for GoogLeNet Network* add-on. For a transfer learning example, see [Transfer Learning Using GoogLeNet](#). For more information, see [googlenet](#).

Long Short-Term Memory (LSTM) Networks: Create deep learning networks with the LSTM recurrent neural network topology for time-series classification and prediction

You can create and train LSTM networks for deep learning. LSTM networks are a type of recurrent neural network (RNN) that learn long-term dependencies between time steps of sequence data.

LSTM networks can be used for the following types of problems:

- Predict labels for a time series (sequence-to-label classification).
- Predict a sequence of labels for a time series (sequence-to-sequence classification).

To create an LSTM network:

- Include a sequence input layer using `sequenceInputLayer`, which inputs time-series data into the network.
- Include an LSTM layer using `lstmLayer`, which defines the LSTM architecture of the network.

For an example showing sequence-to-label classification, see [Classify Sequence Data Using LSTM Networks](#).

You might want to make multiple predictions on parts of a long sequence, or might not have the complete time series in advance. For these tasks, you can make the LSTM network remember and forget the network state between predictions. To configure the state of LSTM networks, use the following functions:

- Make predictions and update the network state using `classifyAndUpdateState` and `predictAndUpdateState`.
- Reset the network state using `resetState`.

To learn more, see [Long Short-Term Memory Networks](#).

Deep Learning Validation: Automatically validate network and stop training when validation metrics stop improving

You can validate deep neural networks at regular intervals during network training, and automatically stop training when validation metrics stop improving.

To perform network validation during training, specify validation data using the 'ValidationData' name-value pair argument of `trainingOptions`. By default, the software validates the network every 50 training iterations by predicting the response of the validation data and calculating the validation loss and accuracy (root mean square error for regression networks). You can change the validation frequency using the 'ValidationFrequency' name-value pair argument.

Network training stops when the validation loss stops improving. By default, if the validation loss is larger than or equal to the previously smallest loss five times in a row, then network training stops. To change the number of times that the validation loss is allowed to not decrease before training stops, use the 'ValidationPatience' name-value pair argument.

For more information, see [Specify Validation Data](#).

Deep Learning Layer Definition: Define new layers with learnable parameters, and specify loss functions for classification and regression output layers

You can define new deep learning layers and specify your own forward propagation, backward propagation, and loss functions. To learn more, see [Define New Deep Learning Layers](#).

- For an example showing how to define a PReLU layer, a layer with learnable parameters, see [Define a Layer with Learnable Parameters](#).
- For an example showing how to define a classification output layer and specify a loss function, see [Define a Classification Output Layer](#).
- For an example showing how to define a regression output layer and specify a loss function, see [Define a Regression Output Layer](#).

Deep Learning Training Plots: Monitor training progress with plots of accuracy, loss, validation metrics, and more

You can monitor deep learning training progress by plotting various metrics during training. Plot accuracy, loss, and validation metrics to determine if and how quickly the network accuracy is improving, and whether the network is starting to overfit the training data. During training, you can

stop training and return the current state of the network by clicking the stop button in the top-right corner. For example, you might want to stop training when the accuracy of the network reaches a plateau and it is clear that the accuracy is no longer improving.

To turn on the training progress plot, use the 'Plots' name-value pair argument of `trainingOptions`. For more information, see [Monitor Deep Learning Training Progress](#).

Deep Learning Image Preprocessing: Efficiently resize and augment image data for training

You can now preprocess images for network training with more options, including resizing, rotation, reflection, and other geometric transformations. To train a network using augmented images, create an `augmentedImageSource` and use it as an input argument to `trainNetwork`. You can configure augmentation options using the `imageDataAugmenter` function. For more information, see [Preprocess Images for Deep Learning](#).

Augmentation helps to prevent the network from overfitting and memorizing the exact details of the training images. It also increases the effective size of the training data set by generating new images based on the training images. For example, use augmentation to generate new images that randomly flip the training images along the vertical axis, and randomly translate the training images horizontally and vertically.

To resize images in other contexts, such as for prediction, classification, and network validation during training, use `imresize`.

Compatibility Considerations

In previous releases, you could perform limited image cropping and reflection using the `DataAugmentation` property of `imageInputLayer`. The `DataAugmentation` property is not recommended. Use `augmentedImageSource` instead.

Bayesian Optimization of Deep Learning: Find optimal settings for training deep networks (Requires Statistics and Machine Learning Toolbox)

Find optimal network parameters and training options for deep learning using Bayesian optimization and the `bayesopt` (Statistics and Machine Learning Toolbox™) function. For an example, see [Deep Learning Using Bayesian Optimization](#).

GoogLeNet Pretrained Network: Transfer learning with pretrained GoogLeNet convolutional neural network

You can now install the Neural Network Toolbox Model *for GoogLeNet Network* add-on.

You can access the model using the `googlenet` function. If the Neural Network Toolbox Model *for GoogLeNet Network* support package is not installed, then the function provides a link to the required support package in the Add-On Explorer. GoogLeNet won the ImageNet Large-Scale Visual Recognition Challenge in 2014. The network is smaller and typically faster than VGG networks, and smaller and more accurate than AlexNet on the ImageNet challenge data set. The network is a directed acyclic graph (DAG) network, and `googlenet` returns the network as a `DAGNetwork` object.

You can use this pretrained model for classification and transfer learning. For an example, see [Transfer Learning Using GoogLeNet](#). For more information on pretrained neural networks in MATLAB, see [Pretrained Convolutional Neural Networks](#).

ResNet-50 and ResNet-101 Pretrained Networks: Transfer learning with pretrained ResNet-50 and ResNet-101 convolutional neural networks

You can now install add-ons for the ResNet-50 and ResNet-101 pretrained convolutional neural networks. To download and install the pretrained networks, use the Add-On Explorer. To learn more about finding and installing add-ons, see [Get Add-Ons \(MATLAB\)](#). You can also download the networks from MathWorks Neural Network Toolbox Team. After you install the add-ons, use the `resnet50` and `resnet101` functions to load the networks, respectively.

To retrain a network on a new classification task, follow the steps of [Transfer Learning Using GoogLeNet](#). Load a ResNet network instead of GoogLeNet, and change the names of the layers that you remove and connect to match the names of the ResNet layers. To extract the layers and architecture of the network for further processing, use `layerGraph`. For more information, see `resnet50` and `resnet101`.

For more information on pretrained neural networks in MATLAB, see [Pretrained Convolutional Neural Networks](#).

Inception-v3 Pretrained Network: Transfer learning with pretrained Inception-v3 convolutional neural network

You can now install the add-on for the Inception-v3 pretrained convolutional neural network. To download and install the pretrained network, use the Add-On Explorer. To learn more about finding and installing add-ons, see [Get Add-Ons \(MATLAB\)](#). You can also download the network from MathWorks Neural Network Toolbox Team. After you install the add-on, use the `inceptionv3` function to load the network.

To retrain the network on a new classification task, follow the steps of [Transfer Learning Using GoogLeNet](#). Load the Inception-v3 network instead of GoogLeNet, and change the names of the layers that you remove and connect to match the names of the Inception-v3 layers. To extract the layers and architecture of the network for further processing, use `layerGraph`. For more information, see `inceptionv3`.

For more information on pretrained neural networks in MATLAB, see [Pretrained Convolutional Neural Networks](#).

Batch Normalization Layer: Speed up network training and reduce sensitivity to network initialization

Use batch normalization layers between convolutional layers and nonlinearities, such as ReLU layers, to speed up network training and reduce the sensitivity to network initialization. Batch normalization layers normalize the activations and gradients propagating through a neural network, making network training an easier optimization problem. To take full advantage of this fact, you can try increasing the learning rate. Because the optimization problem is easier, the parameter updates can be larger and the network can learn faster.

To create a batch normalization layer, use `batchNormalizationLayer`.

Deep Learning: New network layers

You can now use the following layers in deep learning networks:

- Batch normalization layer — Create a layer using `batchNormalizationLayer`.
- Transposed convolution layer — Create a layer using `transposedConv2dLayer`.
- Max unpooling layer — Create a layer using `maxUnpooling2dLayer`.
- Leaky Rectified Linear Unit (ReLU) layer — Create a layer using `leakyReluLayer`.
- Clipped Rectified Linear Unit (ReLU) layer — Create a layer using `clippedReluLayer`.
- Addition layer — Create a layer using `additionLayer`.
- Depth concatenation layer — Create a layer using `depthConcatenationLayer`.
- Sequence input layer for long short-term memory (LSTM) networks — Create a layer using `sequenceInputLayer`.
- LSTM layer — Create a layer using `LSTMLayer`.

Pretrained Models: Import pretrained CNN models and layers from TensorFlow-Keras

You can import pretrained CNN models and weights from TensorFlow-Keras by using the `importKerasNetwork` function. This function imports a Keras model as a `SeriesNetwork` or `DAGNetwork` object, depending on the type of the Keras network. You can then use the imported classification or regression model for prediction or transfer learning on new data.

Alternatively, you can import CNN layers from TensorFlow-Keras by using the `importKerasLayers` function. This function imports the network architecture as a `Layerarray` or `LayerGraph` object. You can then specify the training options using the `trainingOptions` function and train this network using the `trainNetwork` function.

For both `importKerasNetwork` and `importKerasLayers`, you must install the Neural Network Toolbox Importer for *TensorFlow-Keras Models* add-on from the MATLAB® Add-Ons menu.

Functionality Being Removed or Changed

Functionality	Result	Use Instead	Compatibility Considerations
DataAugmentation property of the <code>imageInputLayer</code>	Still runs	<code>augmentedImageSource</code>	The <code>DataAugmentation</code> property of <code>imageInputLayer</code> is not recommended. Use <code>augmentedImageSource</code> instead. For more information, see Preprocess Images for Deep Learning .

Functionality	Result	Use Instead	Compatibility Considerations
Padding property of Convolution2dLayer, MaxPooling2dLayer, and AveragePooling2dLayer objects	Warns	PaddingSize property of Convolution2dLayer, MaxPooling2dLayer, and AveragePooling2dLayer objects	Replace all instances of Padding property with PaddingSize. When you create network layers, use the 'Padding' name-value pair argument to specify the padding. For more information, see Convolution2dLayer, MaxPooling2dLayer, and AveragePooling2dLayer.

R2017a

Version: 10.0

New Features

Bug Fixes

Deep Learning for Regression: Train convolutional neural networks (also known as ConvNets, CNNs) for regression tasks

You can now perform regression for numeric targets (responses) using convolutional neural networks. While defining your network, specify `regressionLayer` as the last layer. Specify the training parameters using the `trainingOptions` function. Train your network using the `trainNetwork` function. To try a regression example showing how to predict angles of rotation of handwritten digits, see [Train a Convolutional Neural Network for Regression](#).

Pretrained Models: Transfer learning with pretrained CNN models AlexNet, VGG-16, and VGG-19, and import models from Caffe (including Caffe Model Zoo)

For pretrained convolutional neural network (CNN) models, AlexNet, VGG-16, and VGG-19, from the MATLAB Add-Ons menu, you can now install the following add-ons:

- Neural Network Toolbox Model *for AlexNet Network*
- Neural Network Toolbox Model *for VGG-16 Network*
- Neural Network Toolbox Model *for VGG-19 Network*

You can access the models using the functions `alexnet`, `vgg16`, and `vgg19`. These models are `SeriesNetwork` objects. You can use these pretrained models for classification and transfer learning.

You can also import other pretrained CNN models from Caffe by using the `importCaffeNetwork` function. This function imports models as a `SeriesNetwork` object. You can then use these models for classifying new data.

Alternatively, you can import CNN layers from Caffe by using the `importCaffeLayers` function. This function imports the layer architecture as a `Layer` array. You can then specify the training options using the `trainingOptions` function and train this network using the `trainNetwork` function.

For both `importCaffeNetwork` and `importCaffeLayers`, you can install the Neural Network Toolbox Importer *for Caffe Models* add-on from the MATLAB® Add-Ons menu.

Deep Learning with Cloud Instances: Train convolutional neural networks using multiple GPUs in MATLAB and MATLAB Distributed Computing Server for Amazon EC2

You can use MATLAB to perform deep learning in the cloud using Amazon Elastic Compute Cloud (Amazon EC2®) with new P2 instances and data stored in the cloud. If you do not have a suitable GPU available for faster training of a convolutional neural network, you can use Amazon Elastic Compute Cloud instead. Try different numbers of GPUs per machine to accelerate training. You can compare and explore the performance of multiple deep neural network configurations to find the best tradeoff of accuracy and memory use. Deep learning in the cloud also requires Parallel Computing Toolbox™. For details, see [Deep Learning in the Cloud](#).

Deep Learning with Multiple GPUs: Train convolutional neural networks on multiple GPUs on PCs (using Parallel Computing Toolbox) and clusters (using MATLAB Distributed Computing Server)

You can now train convolutional neural networks (ConvNets) on multiple GPUs and on clusters. Specify the required hardware using the `ExecutionEnvironment` name-value pair argument in the call to the `trainingOptions` function.

Deep Learning with CPUs: Train convolutional neural networks on CPUs as well as GPUs

You can now train a convolutional neural network (ConvNet) on a CPU using the `trainNetwork` function. If there is no available GPU, by default, then `trainNetwork` uses a CPU to train the network. You can also train a ConvNet on multiple CPU cores on your desktop or a cluster using `'ExecutionEnvironment','parallel'`.

For specifying the hardware on which to train the network, and for system requirements, see the `ExecutionEnvironment` name-value pair argument on `trainingOptions`.

Deep Learning Visualization: Visualize the features ConvNet has learned using deep dream and activations

`deepDreamImage` synthesizes images that strongly activate convolutional neural network (ConvNet) layers using a version of the deep dream algorithm. Visualizing these images highlights the features your trained ConvNet has learned, helping you understand and diagnose network behavior. For examples, see [Deep Dream Images Using AlexNet](#) and [Visualize Features of a Convolutional Neural Network](#).

You can also display network activations on an image to investigate features the network has learned to identify. To try an example, see [Visualize Activations of a Convolutional Neural Network](#).

Table Support: Use data in tables for training of and inference with ConvNets

The `trainNetwork` function and `predict`, `activations`, and `classify` methods now accept data stored in a `table` for classification and regression problems. For details on how to specify your data, see the input argument descriptions on the function and method pages.

Progress Tracking During Training: Specify custom functions for plotting accuracy or stopping at a threshold

When training convolutional neural networks, you can specify one or more custom functions to call at each iteration during training. You can access and act on information during training, for example, to plot accuracy, or stop training early based on a threshold. Specify the functions using the `OutputFcn` name-value pair argument in `trainingOptions`. For examples, see [Plot Training Accuracy During Network Training](#) and [Plot Progress and Stop Training at Specified Accuracy](#).

Deep Learning Examples: Get started quickly with deep learning

New examples and topics help you get started quickly with deep learning in MATLAB.

To find out what tasks you can do, see [Deep Learning in MATLAB](#). To learn about convolutional neural networks and how they work in MATLAB, see:

- [Introduction to Convolutional Neural Networks](#)
- [Specify Layers of Convolutional Neural Network](#)
- [Set Up Parameters and Train Convolutional Neural Network](#)

New examples include:

- [Try Deep Learning in 10 Lines of MATLAB Code](#)
- [Create Simple Deep Learning Network for Classification](#)
- [Transfer Learning and Fine-Tuning of Convolutional Neural Networks](#)
- [Transfer Learning Using AlexNet](#)
- [Feature Extraction Using AlexNet](#)
- [Deep Dream Images Using AlexNet](#)
- [Visualize Activations of a Convolutional Neural Network](#)
- [Visualize Features of a Convolutional Neural Network](#)
- [Create Typical Convolutional Neural Networks](#)
- [Plot Training Accuracy During Network Training](#)
- [Plot Progress and Stop Training at Specified Accuracy](#)
- [Resume Training from a Checkpoint Network](#)
- [Train a Convolutional Neural Network for Regression](#)

R2016b

Version: 9.1

New Features

Bug Fixes

Compatibility Considerations

Deep Learning with CPUs: Run trained CNNs to extract features, make predictions, and classify data on CPUs as well as GPUs

You can choose a CPU to run a pretrained network for extracting features using `activations`, predicting image class scores using `predict`, and estimating image classes using `classify`. To specify the hardware on which to run the network, use the 'ExecutionEnvironment' name-value pair argument in the call to the specific method.

Training a convolutional neural network (ConvNet) requires a GPU. To train a ConvNet, or to run a pretrained network on a GPU, you must have Parallel Computing Toolbox and a CUDA[®]-enabled NVIDIA GPU with compute capability 3.0 or higher.

Deep Learning with Arbitrary Sized Images: Run trained CNNs on images that are different sizes than those used for training

You can run a trained convolutional neural network on arbitrary image sizes to extract features using the `activations` method with `channels` output option. For other output options, the sizes of the images you use in `activations` must be the same as the sizes of the ones used for training. To specify the `channels` output option, use the `OutputAs` name-value pair argument in the call to `activations`.

Performance: Train CNNs faster when using ImageDatastore object

`ImageDatastore` allows batch-reading of JPG or PNG image files using prefetching. This feature enables faster training of convolutional neural networks (ConvNets). If you use a custom function for reading the images, prefetching does not occur.

Deploy Training of Models: Deploy training of a neural network model via MATLAB Compiler or MATLAB Compiler SDK

Use MATLAB Runtime to deploy functions that can train a model. You can deploy MATLAB code that trains neural networks as described in `Create Standalone Application from Command Line` and `Package Standalone Application with Application Compiler App`.

The following methods and functions are NOT supported in deployed mode:

- Training progress dialog, `nntraintool`.
- `genFunction` and `gensim` to generate MATLAB code or Simulink[®] blocks
- `view` method
- `nctool`, `nftool`, `nnstart`, `nprtool`, `ntstool`
- Plot functions (such as `plotperform`, `plottrainstate`, `ploterrhist`, `plotregression`, `plotfit`, and so on)

generateFunction Method: generateFunction generates code for matrices by default

'MatrixOnly' name-value pair argument of `generateFunction` method has no effect. `generateFunction` by default generates code for only matrices.

Compatibility Considerations

You do not need to specify for `generateFunction` to generate code for matrices. Previously, you needed to specify `'MatrixOnly', true`.

alexnet Support Package: Download and use pre-trained convolutional neural network (ConvNet)

You can use pretrained Caffe version of AlexNet convolutional neural network. Download the network from the Add-Ons menu.

For more information about the network, see [Pretrained Convolutional Neural Network](#).

R2016a

Version: 9.0

New Features

Bug Fixes

Deep Learning: Train deep convolutional neural networks with built-in GPU acceleration for image classification tasks (using Parallel Computing Toolbox)

The new functionality enables you to

- Construct convolutional neural network (CNN) architecture (see `Layer`).
- Specify training options using `trainingOptions`.
- Train CNNs using `trainNetwork` for data in 4D arrays or `ImageDatastore`.
- Make predictions of class labels using a trained network using `predict` or `classify`.
- Extract features from a trained network using `activations`.
- Perform transfer learning. That is, retrain the last fully connected layer of an existing CNN on new data.

NOTE: This feature requires the Parallel Computing Toolbox and a CUDA-enabled NVIDIA GPU with compute capability 3.0 or higher.

R2015b

Version: 8.4

New Features

Bug Fixes

Autoencoder neural networks for unsupervised learning of features using the `trainAutoencoder` function

You can train autoencoder neural networks to learn features using the `trainAutoencoder` function. The trained network is an `Autoencoder` object. You can use the trained autoencoder to predict the inputs for new data, using the `predict` method. For all the properties and methods of the object, see the `Autoencoder` class page.

Deep learning using the `stack` function for creating deep networks from autoencoders

You can create deep networks using the `stack` method. To create a deep network, after training the autoencoders, you can

- 1 Extract features from autoencoders using the `encode` method.
- 2 Train a softmax layer for classification using the `trainSoftmaxLayer` function.
- 3 Stack the encoders and the softmax layer to form a deep network, and train the deep network.

The deep network is a `network` object.

Improved speed and memory efficiency for training with Levenberg-Marquardt (`trainlm`) and Bayesian Regularization (`trainbr`) algorithms

An optimized MEX version of the Jacobian backpropagation algorithm allows faster training and reduces memory requirements for training static and open-loop networks using the `trainlm` and `trainbr` functions.

Cross entropy for a single target variable

The `crossentropy` function supports binary encoding, that is, when there are only two classes and $N = 1$ (N is the number of rows in the `targets` input argument).

R2015a

Version: 8.3

New Features

Bug Fixes

Progress update display for parallel training

The Neural Network Training tool (nntraintool) now displays progress updates when conducting parallel training of a network.

R2014b

Version: 8.2.1

Bug Fixes

R2014a

Version: 8.2

New Features

Bug Fixes

Training panels for Neural Fitting Tool and Neural Time Series Tool Provide Choice of Training Algorithms

The training panels in the Neural Fitting and Neural Time Series tools now let you select a training algorithm before clicking **Train**. The available algorithms are:

- Levenberg-Marquardt (`trainlm`)
- Bayesian Regularization (`trainbr`)
- Scaled Conjugate Gradient (`trainscg`)

For more information on using Neural Fitting, see [Fit Data with a Neural Network](#).

For more information on using Neural Time Series, see [Neural Network Time Series Prediction and Modeling](#).

Bayesian Regularization Supports Optional Validation Stops

Because Bayesian-Regularization with `trainbr` can take a long time to stop, validation used with Bayesian-Regularization allows it to stop earlier, while still getting some of the benefits of weight regularization. Set the training parameter `trainParam.max_fail` to specify when to make a validation stop. Validation is disabled for `trainbr` by default when `trainParam.max_fail` is set to 0.

For example, to train as before without validation:

```
[x,t] = house_dataset;  
net = feedforwardnet(10,'trainbr');  
[net,tr] = train(net,x,t);
```

To train with validation:

```
[x,t] = house_dataset;  
net = feedforwardnet(10,'trainbr');  
net.trainParam.max_fail = 6;  
[net,tr] = train(net,x,t);
```

Neural Network Training Tool Shows Calculations Mode

Neural Network Training Tool now shows its calculations mode (i.e., MATLAB, GPU) in its **Algorithms** section.

R2013b

Version: 8.1

New Features

Bug Fixes

Compatibility Considerations

Function code generation for application deployment of neural network simulation (using MATLAB Coder, MATLAB Compiler, and MATLAB Builder products)

- “New Function: genFunction” on page 14-2
- “Enhanced Tools” on page 14-3

New Function: genFunction

The function `genFunction` generates a stand-alone MATLAB function for simulating any trained neural network and preparing it for deployment in many scenarios:

- Document the input-output transforms of a neural network used as a calculation template for manual reimplementations of the network
- Create a Simulink block using the MATLAB Function block
- Generate C/C++ code with MATLAB Coder™ `codegen`
- Generate efficient MEX-functions with MATLAB Coder `codegen`
- Generate stand-alone C executables with MATLAB Compiler™ `mcc`
- Generate C/C++ libraries with MATLAB Compiler `mcc`
- Generate Excel® and .COM components with MATLAB Builder™ EX `mcc` options
- Generate Java components with MATLAB Builder JA `mcc` options
- Generate .NET components with MATLAB Builder NE `mcc` options

`genFunction(net, 'path/name')` takes a neural network and file path and produces a standalone MATLAB function file `'name.m'`.

`genFunction(____, 'MatrixOnly', 'yes')` overrides the default cell/matrix notation and instead generates a function that uses only matrix arguments compatible with MATLAB Coder tools. For static networks the matrix columns are interpreted as independent samples. For dynamic networks the matrix columns are interpreted as a series of time steps. The default value is `'no'`.

`genFunction(____, 'ShowLinks', 'no')` disables the default behavior of displaying links to generated help and source code. The default is `'yes'`.

Here a static network is trained and its outputs calculated.

```
[x,t] = house_dataset;
houseNet = feedforwardnet(10);
houseNet = train(houseNet,x,t);
y = houseNet(x);
```

A MATLAB function with the same interface as the neural network object is generated and tested, and viewed.

```
genFunction(houseNet, 'houseFcn');
y2 = houseFcn(x);
accuracy2 = max(abs(y-y2))
edit houseFcn
```

The new function can be compiled with the MATLAB Compiler tools (license required) to a shared/dynamically linked library with `mcc`.

```
mcc -W lib:libHouse -T link:lib houseFcn
```

Next, another version of the MATLAB function is generated which supports only matrix arguments (no cell arrays). This function is tested. Then it is used to generate a MEX-function with the MATLAB Coder tool `codegen` (license required) which is also tested.

```
genFunction(houseNet, 'houseFcn', 'MatrixOnly', 'yes');
y3 = houseFcn(x);
accuracy3 = max(abs(y-y3))

x1Type = coder.typeof(double(0), [13 Inf]); % Coder type of input 1
codegen houseFcn.m -config:mex -o houseCodeGen -args {x1Type}
y4 = houseCodeGen(x);
accuracy4 = max(abs(y-y4))
```

Here, a dynamic network is trained and its outputs calculated.

```
[x,t] = maglev_dataset;
maglevNet = narxnet(1:2,1:2,10);
[X,Xi,Ai,T] = preparets(maglevNet,x,{},t);
maglevNet = train(maglevNet,X,T,Xi,Ai);
[y,xf,af] = maglevNet(X,Xi,Ai);
```

Next, a MATLAB function is generated and tested. The function is then used to create a shared/dynamically linked library with `mcc`.

```
genFunction(maglevNet, 'maglevFcn');
[y2,xf,af] = maglevFcn(X,Xi,Ai);
accuracy2 = max(abs(cell2mat(y)-cell2mat(y2)))
mcc -W lib:libMaglev -T link:lib maglevFcn
```


Next, another version of the MATLAB function is generated which supports only matrix arguments (no cell arrays). This function is tested. Then it is used to generate a MEX-function with the MATLAB Coder tool `codegen`, and the result is also tested.

```
genFunction(maglevNet, 'maglevFcn', 'MatrixOnly', 'yes');
x1 = cell2mat(X(1,:)); % Convert each input to matrix
x2 = cell2mat(X(2,:));
xi1 = cell2mat(Xi(1,:)); % Convert each input state to matrix
xi2 = cell2mat(Xi(2,:));
[y3,xf1,xf2] = maglevFcn(x1,x2,xi1,xi2);
accuracy3 = max(abs(cell2mat(y)-y3))


x1Type = coder.typeof(double(0), [1 Inf]); % Coder type of input 1
x2Type = coder.typeof(double(0), [1 Inf]); % Coder type of input 2
xi1Type = coder.typeof(double(0), [1 2]); % Coder type of input 1 states
xi2Type = coder.typeof(double(0), [1 2]); % Coder type of input 2 states
codegen maglevFcn.m -config:mex -o maglevNetCodeGen -args {x1Type x2Type xi1Type xi2Type}
[y4,xf1,xf2] = maglevNetCodeGen(x1,x2,xi1,xi2);
dynamic_codegen_accuracy = max(abs(cell2mat(y)-y4))
```

Enhanced Tools

The function `genFunction` is introduced with a new panel in the tools `nftool`, `nctool`, `nprtool` and `ntstool`.



The advanced scripts generated on the Save Results panel of each of these tools includes an example of deploying networks with `genFunction`.



For more information, see [Deploy Neural Network Functions](#).

Enhanced multi-timestep prediction for switching between open-loop and closed-loop modes with NARX and NAR neural networks

Dynamic networks with feedback, such as `narxnet` and `narnet` neural networks, can be transformed between open-loop and closed-loop modes with the functions `openloop` and `closeloop`. Closed-loop networks make multistep predictions. In other words, they continue to predict when external feedback is missing, by using internal feedback.

It can be useful to simulate a trained neural network up the present with all the known values of a time-series in open-loop mode, then switch to closed-loop mode to continue the simulation for as many predictions into the future as are desired. It is now much easier to do this.

Previously, `openloop` and `closeloop` transformed the neural network between those two modes.


```
net = openloop(net)
net = closeloop(net)
```

This is still the case. However, these functions now also support the transformation of input and layer delay state values between open- and closed-loop modes, making switching between closed-loop to open-loop multistep prediction easier.

```
[net,xi,ai] = openloop(net,xi,ai);
[net,xi,ai] = closeloop(net,xi,ai);
```


Here, a neural network is trained to model the magnetic levitation system in default open-loop mode.

```
[X,T] = maglev_dataset;
net = narxnet(1:2,1:2,10);
[x,xi,ai,t] = preparets(net,X,{},T);
net = train(net,x,t,xi,ai);
view(net)
```



Then `closeloop` is used to convert the network to closed-loop form for simulation.

```
netc = closeloop(net);
[x,xi,ai,t] = preparets(netc,X,{},T);
y = netc(x,xi,ai);
view(netc)
```



Now consider the case where you might have a record of the Maglev's behavior for 20 time steps, but then want to predict ahead for 20 more time steps beyond that.

Define the first 20 steps of inputs and targets, representing the 20 time steps where the output is known, as defined by the targets `t`. Then the next 20 time steps of the input are defined, but you use the network to predict the 20 outputs using each of its predictions feedback to help the network perform the next prediction.

```
x1 = x(1:20);
t1 = t(1:20);
x2 = x(21:40);
```

Then simulate the open-loop neural network on this data:

```
[x,xi,ai,t] = preparets(net,x1,{},t1);
[y1,xf,af] = net(x,xi,ai);
```

Now the final input and layer states returned by the network are converted to closed-loop form along with the network. The final input states `xf`, and layer states `af`, of the open-loop network become the initial input states `xi`, and layer states `ai`, of the closed-loop network.

```
[netc,xi,ai] = closeloop(net,xf,af);
```

Typically, `preparets` is used to define initial input and layer states. Since these have already been obtained from the end of the open-loop simulation, you do not need `preparets` to continue with the 20 step predictions of the closed-loop network.

```
[y2,xf,af] = netc(x2,xi,ai);
```

Note that `x2` can be set to different sequences of inputs to test different scenarios for however many time steps you would like to make predictions. For example, to predict the magnetic levitation system's behavior if 10 random inputs were used:

```
x2 = num2cell(rand(1,10));  
[y2,xf,af] = netc(x2,xi,ai);
```

For more information, see [Multistep Neural Network Prediction](#).

Cross-entropy performance measure for enhanced pattern recognition and classification accuracy

Networks created with `patternnet` now use the cross-entropy performance measure (`crossentropy`), which frequently produces classifiers with fewer percentage misclassifications than obtained using mean squared error.

See “Softmax transfer function in output layer gives consistent class probabilities for pattern recognition and classification” on page 14-6.

Softmax transfer function in output layer gives consistent class probabilities for pattern recognition and classification

`patternnet`, which you use to create a neural network suitable for learning classification problems, has been improved in two ways.

First, networks created with `patternnet` now use the cross-entropy performance measure (`crossentropy`), which frequently produces classifiers with fewer percentage misclassifications than obtained using mean squared error.


Second, `patternnet` returns networks that use the Soft Max transfer function (`softmax`) for the output layer instead of the `tansig` sigmoid transfer function. `softmax` results in output vectors normalized so they sum to 1.0, that can be interpreted as class probabilities. (`tansig` also produces outputs in the 0 to 1 range, but they do not sum to 1.0 and have to be manually normalized before being treated as consistent class probabilities.)

Here a `patternnet` with 10 neurons is created, its performance function and diagram are displayed.

```
net = patternnet(10);  
net.performFcn
```

```
ans =  
crossentropy
```



view(net)



The output layer's transfer function is shown with the symbol for softmax.

Training the network takes advantage of the new crossentropy performance function. Here the network is trained to classify iris flowers. The cross-entropy performance algorithm is shown in the nntaintool algorithm section. Clicking the "Performance" plot button shows how the network's cross-entropy was minimized throughout the training session.

```
[x,t] = iris_dataset;  
net = train(net,x,t);
```



Simulating the network results in normalized output. Sample 150 is used to illustrate the normalization of class membership likelihoods:

```
y = net(x(:,150))
```

```
y =
```

```
0.0001  
0.0528  
0.9471
```

```
sum(y)
```

```
1
```

The network output shows three membership probabilities with class three as by far the most likely. Each probability value is between 0 and 1, and together they sum to 1 indicating the 100% probability that the input $x(:,150)$ falls into one of the three classes.

Compatibility Considerations

If a patternnet network is used to train on target data with only one row, the network's output transfer function will be changed to tansig and its outputs will continue to operate as they did

before the `softmax` enhancement. However, the 1-of-N notation for targets is recommended even when there are only two classes. In that case the targets should have two rows, where each column has a 1 in the first or second row to indicate class membership.

If you prefer the older `patternnet` of mean squared error performance and a sigmoid output transfer function, you can specify this by setting those neural network object properties. Here is how that is done for a `patternnet` with 10 neurons.

```
net = patternnet(10);
net.layers{2}.transferFcn = 'tansig';
net.performFcn = 'mse';
```

Automated and periodic saving of intermediate results during neural network training

Intermediate results can be periodically saved during neural network training to a `.mat` file for recovery if the computer fails or the training process is killed. This helps protect the values of long training runs, which if interrupted, would otherwise need to be completely restarted.

This feature can be especially useful for long parallel training sessions that are more likely to be interrupted by computing resource failures and which you can stop only with a Ctrl+C break, because the `nntraintool` tool (with its **Stop** button) is not available during parallel training.

Checkpoint saves are enabled with an optional `'CheckpointFile'` training argument followed by the checkpoint file's name or path. If only a file name is specified, it is placed in the current folder by default. The file must have the `.mat` file extension, but if it is not specified it is automatically added. In this example, checkpoint saves are made to a file called `MyCheckpoint.mat` in the current folder.

```
[x,t] = house_dataset;
net = feedforwardnet(10);
net2 = train(net,x,t,'CheckpointFile','MyCheckpoint.mat');
```

```
22-Mar-2013 04:49:05 First Checkpoint #1: /WorkingDir/MyCheckpoint.mat
22-Mar-2013 04:49:06 Final Checkpoint #2: /WorkingDir/MyCheckpoint.mat
```

By default, checkpoint saves occur at most once every 60 seconds. For the short training example above this results in only two checkpoints, one at the beginning and one at the end of training.

The optional training argument `'CheckpointDelay'` changes the frequency of saves. For example, here the minimum checkpoint delay is set to 10 seconds, for a time-series problem where a neural network is trained to model a levitated magnet.

```
[x,t] = maglev_dataset;
net = narxnet(1:2,1:2,10);
[X,Xi,Ai,T] = preparets(net,x,{},t);
net2 = train(net,X,T,Xi,Ai,'CheckpointFile','MyCheckpoint.mat','CheckpointDelay',10);
```

```
22-Mar-2013 04:59:28 First Checkpoint #1: /WorkingDir/MyCheckpoint.mat
22-Mar-2013 04:59:38 Write Checkpoint #2: /WorkingDir/MyCheckpoint.mat
22-Mar-2013 04:59:48 Write Checkpoint #3: /WorkingDir/MyCheckpoint.mat
22-Mar-2013 04:59:58 Write Checkpoint #4: /WorkingDir/MyCheckpoint.mat
22-Mar-2013 05:00:08 Write Checkpoint #5: /WorkingDir/MyCheckpoint.mat
22-Mar-2013 05:00:09 Final Checkpoint #6: /WorkingDir/MyCheckpoint.mat
```

After a computer failure or training interruption, the checkpoint structure containing the best neural network obtained before the interruption and the training record can be reloaded. In this case the `stage` field value is `'Final'`, indicating the last save was at the final epoch, because training

completed successfully. The first epoch checkpoint is indicated by 'First', and intermediate checkpoints by 'Write'.

```
load('MyCheckpoint.mat')

checkpoint =

    file: '/WorkingDir/MyCheckpoint.mat'
    time: [2013 3 22 5 0 9.0712]
    number: 6
    stage: 'Final'
    net: [1x1 network]
    tr: [1x1 struct]
```

Training can be resumed from the last checkpoint by reloading the dataset (if necessary), then calling `train` with the recovered network.

```
net = checkpoint.net;
[x,t] = maglev_dataset;
load('MyCheckpoint.mat');
[X,Xi,Ai,T] = preparets(net,x,{},t);
net2 = train(net,X,T,Xi,Ai,'CheckpointFile','MyCheckpoint.mat','CheckpointDelay',10);
```

For more information, see [Automatically Save Checkpoints During Neural Network Training](#).

Simpler Notation for Networks with Single Inputs and Outputs

The majority of neural networks have a single input and single output. You can now refer to the input and output of such networks with the properties `net.input` and `net.output`, without the need for cell array indices.

Here a feed-forward neural network is created and its input and output properties examined.

```
net = feedforwardnet(10);
net.input
net.output
```

The `net.inputs{1}` notation for the input and `net.outputs{2}` notation for the second layer output continue to work. The cell array notation continues to be required for networks with multiple inputs and outputs.

For more information, see [Neural Network Object Properties](#).

Neural Network Efficiency Properties Are Now Obsolete

The neural network property `net. efficiency` is no longer shown when a network object properties are displayed. The following line of code displays the properties of a feed-forward network.

```
net = feedforwardnet(10)
```

Compatibility Considerations

The efficiency properties are still supported and do not yet generate warnings, so backward compatibility is maintained. However the recommended way to use memory reduction is no longer to set `net. efficiency. memoryReduction`. The recommended notation since R2012b is to use optional training arguments:

```
[x,t] = vinyl_dataset;  
net = feedforwardnet(10);  
net = train(net,x,t,'Reduction',10);
```

Memory reduction is a way to trade off training time for lower memory requirements when using Jacobian training such as `trainlm` and `trainbr`. The `MemoryReduction` value indicates how many passes must be made to simulate the network and calculate its gradients each epoch. The storage requirements go down as the memory reduction goes up, although not necessarily proportionally. The default `MemoryReduction` is 1, which indicates no memory reduction.

R2013a

Version: 8.0.1

Bug Fixes

R2012b

Version: 8.0

New Features

Bug Fixes


Compatibility Considerations

Speed and memory efficiency enhancements for neural network training and simulation

The neural network simulation, gradient, and Jacobian calculations are reimplemented with native MEX-functions in Neural Network Toolbox Version 8.0. This results in faster speeds, especially for small to medium network sizes, and for long time-series problems.

In Version 7, typical code for training and simulating a feed-forward neural network looks like this:

```
[x,t] = house_dataset;
net = feedforwardnet(10);
view(net)
net = train(net,x,t);
y = net(x);
```




In Version 8.0, the above code does not need to be changed, but calculations now happen in compiled native MEX code.

Speedups of as much as 25% over Version 7.0 have been seen on a sample system (4-core 2.8 GHz Intel i7 with 12 GB RAM).

Note that speed improvements measured on the sample system might vary significantly from improvements measured on other systems due to different chip speeds, memory bandwidth, and other hardware and software variations.

The following code creates, views, and trains a dynamic NARX neural network model of a maglev system in open-loop mode.

```
[x,t] = maglev_dataset;
net = narxnet(1:2,1:2,10);
view(net)
[X,Xi,Ai,T] = preparets(net,x,{},t);
net = train(net,X,T,Xi,Ai);
y = net(X,Xi,Ai)
```



The following code measures training speed over 10 training sessions, with the training window disabled to avoid GUI timing interference.

On the sample system, this ran three times (3x) faster in Version 8.0 than in Version 7.0.


```
rng(0)
[x,t] = maglev_dataset;
net = narxnet(1:2,1:2,10);
```



```

[X,Xi,Ai,T] = preparets(net,x,{},t);
net.trainParam.showWindow = false;
tic
for i=1:10
    net = train(net,X,T,Xi,Ai);
end
toc

```



The following code trains the network in closed-loop mode:


```


[x,t] = maglev_dataset;
net = narxnet(1:2,1:2,10);
net = closeloop(net);
view(net)
[X,Xi,Ai,T] = preparets(net,x,{},t);
net = train(net,X,T,Xi,Ai);

```

For this case, and most closed-loop (recurrent) network training, Version 8.0 ran the code more than one-hundred times (100x) faster than Version 7.0.

A dramatic example of where the improved closed loop training speed can help is when training a NARX network model of a double pendulum. By initially training the network in open-loop mode, then in closed-loop mode with two time step sequences, then three time step sequences, etc., a network has been trained that can simulate the system for 500 time steps in closed-loop mode. This corresponds to a 500 step ahead prediction.





Because of the Version 8.0 MEX speedup, this only took a few hours, as opposed to the months it would have taken in Version 7.0.

MEX code is also far more memory efficient. The amount of RAM used for intermediate variables during training and simulation is now relatively constant, instead of growing linearly with the number of samples. In other words, a problem with 10,000 samples requires the same temporary storage as a problem with only 100 samples.

This memory efficiency means larger problems can be trained on a single computer.

Compatibility Considerations

For very large networks, MEX code might fall back to MATLAB code. If this happens and memory availability becomes an issue, use the `'reduction'` option to implement memory reduction. The reduction number indicates the number of passes to make through the data for each calculation. Each pass calculates with a fraction of the data, and the results are combined after all passes are complete. This trades off lower memory requirements for longer calculation times.

```
net = train(net,x,t,'reduction',10);
y = net(x,'reduction',10);
```

The previous way to indicate memory reduction was to set the `net. efficiency. memoryReduction` property before training:


```
net. efficiency. memoryReduction = N;
```

This continues to work in Version 8.0, but it is recommended that you update your code to use the `'reduction'` option for train and network simulation. Additional name-value pair arguments are the standard way to indicate calculation options.

Speedup of training and simulation with multicore processors and computer clusters using Parallel Computing Toolbox

Parallel Computing Toolbox allows Neural Network Toolbox simulation, and gradient and Jacobian calculations to be parallelized across multiple CPU cores, reducing calculation times. Parallelization

splits the data among several workers. Results for the whole dataset are combined after all workers have completed their calculations.



Note that, during training, the calculation of network outputs, performance, gradient, and Jacobian calculations are parallelized, while the main training code remains on one worker.

To train a network on the `house_dataset` problem, introduced above, open a local MATLAB pool of workers, then call `train` and `sim` with the new `'useParallel'` option set to `'yes'`.

```
matlabpool open
numWorkers = matlabpool('size')
```

If calling `matlabpool` produces an error, it might be that Parallel Computing Toolbox is not available.

```
[x,t] = house_dataset;
net = feedforwardnet(10);
net = train(net,x,t,'useParallel','yes');
y = sim(net,'useParallel','yes');
```

On the sample system with a pool of four cores, typical speedups have been between 3x and 3.7x. Using more than four cores might produce faster speeds. For more information, see Parallel and GPU Computing.

GPU computing support for training and simulation on single and multiple GPUs using Parallel Computing Toolbox

Parallel Computing Toolbox allows Neural Network Toolbox simulation and training to be parallelized across the multiprocessors and cores of a graphics processing unit (GPU).

To train and simulate with a GPU set the 'useGPU' option to 'yes'. Use the `gpuDevice` command to get information on your GPU.

```
gpuInfo = gpuDevice
```

If calling `gpuDevice` produces an error, it might be that Parallel Computing Toolbox is not available.

Training on GPUs cannot be done with Jacobian algorithms, such as `trainlm` or `trainbr`, but it can be done with any of the gradient algorithms such as `trainscg`. If you do not change the training function, it will happen automatically.

```
[x,t] = house_dataset;  
net = feedforwardnet(10);  
net.trainFcn = 'trainscg';  
net = train(net,x,t,'useGPU','yes');  
y = sim(net,'useGPU','yes');
```

Speedups on the sample system with an nVidia GTX 470 GPU card have been between 3x and 7x, but might increase as GPUs continue to improve.

You can also use multiple GPUs. If you set both 'useParallel' and 'useGPU' to 'yes', any worker associated with a unique GPU will use that GPU, and other workers will use their CPU core. It is not efficient to share GPUs between workers, as that would require them to perform their calculations in sequence instead of in parallel.

```
numWorkers = matlabpool('size')  
numGPUs = gpuDeviceCount  
  
[x,t] = house_dataset;  
net = feedforwardnet(10);  
net.trainFcn = 'trainscg';  
net = train(net,x,t,'useParallel','yes','useGPU','yes');  
y = sim(net,'useParallel','yes','useGPU','yes');
```

Tests with three GPU workers and one CPU worker on the sample system have seen 3x or higher speedup. Depending on the size of the problem, and how much it uses the capacity of each GPU, adding GPUs might increase speed or might simply increase the size of problem that can be run.

In some cases, training with both GPUs and CPUs can result in slower speeds than just training with the GPUs, because the CPUs might not keep up with the GPUs. In this case, set 'useGPU' to 'only' and only GPU workers will be used.

```
[x,t] = house_dataset;  
net = feedforwardnet(10);  
net = train(net,x,t,'useParallel','yes','useGPU','only');  
y = sim(net,'useParallel','yes','useGPU','only');
```

For more information, see [Parallel and GPU Computing](#).

Distributed training of large datasets on computer clusters using MATLAB Distributed Computing Server

Besides allowing load balancing, Composite data also allows datasets too large to fit within the RAM of a single computer to be distributed across the RAM of a cluster.

This is done by loading the Composite sequentially. For instance, here the sub-datasets are loaded from files as they are distributed:

```
Xc = Composite;
Tc = Composite;
for i=1:10
    data = load(['dataset' num2str(i)])
    Xc{i} = data.x;
    Tc{i} = data.t;
    clear data
end
```

This technique allows for training with datasets of any size, limited only by the available RAM across an entire cluster.


For more information, see Parallel and GPU Computing.

Elliot sigmoid transfer function for faster simulation

The new transfer function `elliotsig` calculates its output without using the `exp` function used by both `tansig` and `logsig`. This lets it execute much faster, especially on deployment hardware that might either not support `exp` or which implements it with software that takes many more execution cycles than simple arithmetic operations.


This example displays a plot of `elliotsig` alongside `tansig`:

```
n = -10:0.01:10;
a1 = elliotsig(n);
a2 = tansig(n);
h = plot(n,a1,n,a2);
legend(h, 'ELLIOTSIG', 'TANSIG', 'Location', 'NorthWest')
```




To set up a neural network to use the `elliotsig` transfer function, change each `tansig` layer's transfer function with its `transferFcn` property. For instance, here a network using `elliotsig` is created, viewed, trained, and simulated:

```
[x,t] = house_dataset;
net = feedforwardnet(10);
view(net) % View TANSIG network
```



```
net.layers{1}.transferFcn = 'elliotsig';
view(net) % View ELLIOTSIG network
```



```
net = train(net,x,t);
y = net(x)
```

The `elliotsig` transfer function might be even faster on an Intel processor.

```
n = rand(1000,1000);
tic, for i=1:100, a = elliotsig(n); end, elliotsigTime = toc
tic, for i=1:100, a = tansig(n); end, tansigTime = toc
speedup = tansigTime / elliotsigTime
```


On one system the speedup was almost 3x.

However, because of the different shape, `elliotsig` might not result in faster training than `tansig`. It might require more training steps. For simulation, `elliotsig` is always faster.

For more information, see [Fast Elliot Sigmoid](#).

Faster training and simulation with computer clusters using MATLAB Distributed Computing Server

If a MATLAB pool is opened using a cluster of computers, the previous parallel training and simulations happen across the CPU cores and GPUs of all the computers in the pool. For problems with hundreds of thousands or millions of samples, this might result in considerable speedup.



For more information, see [Parallel and GPU Computing](#).

Load balancing parallel calculations

When training and simulating a network using the 'useParallel' option, the dataset is automatically divided into equal parts across the workers. However, if different workers have different speed and memory limitations, it can be helpful to adjust the amount of data sent to each worker, so that the faster workers or those with more memory have proportionally more data.

This is done using the Parallel Computing Toolbox function `Composite`. `Composite` data is data spread across a parallel pool of MATLAB workers.


For instance, if a parallel pool is open with four workers, data can be distributed as follows:

```
[x,t] = house_dataset;
Xc = Composite;
Tc = Composite;
Xc{1} = x(:, 1:150); % First 150 samples of x
Tc{1} = t(:, 1:150); % First 150 samples of t
Xc{2} = x(:, 151:300); % Second 150 samples of x
Tc{2} = t(:, 151:300); % Second 150 samples of t
Xc{3} = x(:, 301:403); % Third 103 samples of x
Tc{3} = t(:, 301:403); % Third 103 samples of t
```

```
Xc{4} = x(:, 404:506); % Fourth 103 samples of x
Tc{4} = t(:, 404:506); % Fourth 103 samples of t
```

When you call `train`, the `'useParallel'` option is not needed, because `train` automatically trains in parallel when using Composite data.

```
net = train(net,Xc,Tc);
```



If you want workers 1 and 2 to use GPU devices 1 and 2, while workers 3 and 4 use CPUs, set up data for workers 1 and 2 using `nndata2gpu` inside an `spmd` clause.

```
spmd
    if labindex <= 2
        Xc = nndata2gpu(Xc);
        Tc = nndata2gpu(Tc);
    end
end
```

The function `nndata2gpu` takes a neural network matrix or cell array time series data and converts it to a properly sized `gpuArray` on the worker's GPU. This involves transposing the matrices, padding the columns so their first elements are memory aligned, and combining matrices, if the data was a cell array of matrices. To reverse process outputs returned after simulation with `gpuArray` data, use `gpu2nndata` to convert back to a regular matrix or a cell array of matrices.

As with `'useParallel'`, the data type removes the need to specify `'useGPU'`. Training and simulation automatically recognize that two of the workers have `gpuArray` data and employ their GPUs accordingly.

```
net = train(net,Xc,Tc);
```

This way, any variation in speed or memory limitations between workers can be accounted for by putting differing numbers of samples on those workers.

For more information, see [Parallel and GPU Computing](#).

Summary and fallback rules of computing resources used from `train` and `sim`

The convention used for computing resources requested by options `'useParallel'` and `'useGPU'` is that if the resource is available it will be used. If it is not, calculations still occur accurately, but without that resource. Specifically:

- 1 If `'useParallel'` is set to `'yes'`, but no MATLAB pool is open, then computing occurs in the main MATLAB thread and is not distributed across workers.
- 2 If `'useGPU'` is set to `'yes'`, but there is not a supported GPU device selected, then computing occurs on the CPU.

-
- 3 If 'useParallel' and 'useGPU' are set to 'yes', each worker uses a GPU if it is the first worker with a particular supported GPU selected, or uses a CPU core otherwise.
 - 4 If 'useParallel' is set to 'yes' and 'useGPU' is set to 'only', then only the first worker with a supported GPU is used, and other workers are not used. However, if no GPUs are available, calculations revert to parallel CPU cores.

Set the 'showResources' option to 'yes' to check what resources are actually being used, as opposed to requested for use, when training and simulating.

Example 16.1. Example: View computing resources

```
[x,t] = house_dataset;  
net = feedforwardnet(10);
```

```
net2 = train(net,x,t,'showResources','yes');  
y = net2(x,'showResources','yes');
```

```
Computing Resources:  
MEX on PCWIN64
```

```
net2 = train(net,x,t,'useParallel','yes','showResources','yes');  
y = net2(x,'useParallel','yes','showResources','yes');
```

```
Computing Resources:  
Worker 1 on Computer1, MEX on PCWIN64  
Worker 2 on Computer1, MEX on PCWIN64  
Worker 3 on Computer1, MEX on PCWIN64  
Worker 4 on Computer1, MEX on PCWIN64
```

```
net2 = train(net,x,t,'useGPU','yes','showResources','yes');  
y = net2(x,'useGPU','yes','showResources','yes');
```

```
Computing Resources:  
GPU device 1, TypeOfCard
```

```
net2 = train(net,x,t,'useParallel','yes','useGPU','yes',...  
                'showResources','yes');  
y = net2(x,'useParallel','yes','useGPU','yes','showResources','yes');
```

```
Computing Resources:  
Worker 1 on Computer1, GPU device 1, TypeOfCard  
Worker 2 on Computer1, GPU device 2, TypeOfCard  
Worker 3 on Computer1, MEX on PCWIN64  
Worker 4 on Computer1, MEX on PCWIN64
```

```
net2 = train(net,x,t,'useParallel','yes','useGPU','only',...  
                'showResources','yes');  
y = net2(x,'useParallel','yes','useGPU','only','showResources','yes');
```

```
Computing Resources:  
Worker 1 on Computer1, GPU device 1, TypeOfCard  
Worker 2 on Computer1, GPU device 2, TypeOfCard
```

Updated code organization

The code organization for data processing, weight, net input, transfer, performance, distance and training functions are updated. Custom functions of these kinds need to be updated to the new organization.

In Version 8.0 the related functions for neural network processing are in package folders, so each local function has its own file.

For instance, in Version 7.0 the function `tansig` contained a large switch statement and several local functions. In Version 8.0 there is a root function `tansig`, along with several package functions in the folder `/toolbox/nnet/nnet/nntransfer/+tansig/`.

```
+tansig/activeInputRange.m
+tansig/apply.m
+tansig/backprop.m
+tansig/da_dn.m
+tansig/discontinuity.m
+tansig/forwardprop.m
+tansig/isScalar.m
+tansig/name.m
+tansig/outputRange.m
+tansig/parameterInfo.m
+tansig/simulinkParameters.m
+tansig/type.m
```

Each transfer function has its own package with the same set of package functions. For lists of processing, weight, net input, transfer, performance, and distance functions, each of which has its own package, type the following:

```
help nnprocess
help nnweight
help nnnetinput
help nntransfer
help nnperformance
help nndistance
```

The calling interfaces for training functions are updated for the new calculation modes and parallel support. Normally, training functions would not be called directly, but indirectly by `train`, so this is unlikely to require any code changes.

Compatibility Considerations

Due to the new package organization for processing, weight, net input, transfer, performance and distance functions, any custom functions of these types will need to be updated to conform to this new package system before they will work with Version 8.0.

See the main functions and package functions for `mapminmax`, `dotprod`, `netsum`, `tansig`, `mse`, and `dist` for examples of this new organization. Any of these functions and its package functions may be used as a template for new or updated custom functions.

Due to the new calling interfaces for training functions, any custom backpropagation training function will need to be updated to work with Version 8.0. See `trainlm` and `trainscg` for examples that can be used as templates for any new or updated custom training function.

R2012a

Version: 7.0.3

Bug Fixes

R2011b

Version: 7.0.2

Bug Fixes

R2011a

Version: 7.0.1

Bug Fixes

R2010b

Version: 7.0


New Features

Bug Fixes


Compatibility Considerations

New Neural Network Start GUI

The new `nnstart` function opens a GUI that provides links to new and existing Neural Network Toolbox GUIs and other resources. The first panel of the GUI opens four "getting started" wizards.




The second panel provides links to other toolbox starting points.




New Time Series GUI and Tools


The new `ntstool` function opens a wizard GUI that allows time series problems to be solved with three kinds of neural networks: NARX networks (neural auto-regressive with external input), NAR networks (neural auto-regressive), and time delay neural networks. It follows a similar format to the neural fitting (`nftool`), clustering (`nctool`), and pattern recognition (`nprtool`) tools.



Network diagrams shown in the Neural Time Series Tool, Neural Training Tool, and with the `view(net)` command, have been improved to show tap delay lines in front of weights, the sizes of inputs, layers and outputs, and the time relationship of inputs and outputs. Open loop feedback outputs and inputs are indicated with matching tabs and indents in their respective blocks.



The Save Results panel of the Neural Network Time Series Tool allows you to generate both a Simple Script, which demonstrates how to get the same results as were obtained with the wizard, and an Advanced Script, which provides an introduction to more advanced techniques.



```


Editor - unsaved
File Edit Text Go Cell Tools Debug Desktop Window Help
x 1.0 1.1
% Solve an Autoregressive Problem with External Input with a NNARX Neural Network
% Script generated by nntool
% Created Thu Jun 19 18:19:04 EDT 2010
%
% This script assumes three variables are defined:
%
% simpleNARXInputs - input time series.
% simpleNARXTargets - feedback time series.
%
10 inputSeries = simpleNARXInputs;
11 targetSeries = simpleNARXTargets;
12
13 % Create a Nonlinear Autoregressive Network with External Input
14 inputDelays = 1:1;
15 feedbackDelays = 1:1;
16 hiddenLayerSize = 20;
17 net = narnet(inputDelays,feedbackDelays,hiddenLayerSize);
18
19 % Prepare the data for training and simulation
20 % The function PREPARETS prepares timeseries data for a particular network
21 % shifting time by the minimum amount to fill input states and layer states
22 % Using PREPARETS allows you to keep your original time series data unchan
23 % easily customizing it for networks with differing numbers of delays, wit
24 % open loop or closed loop feedback modes.
25 [inputs,inputStates,layerStates,targets] = preparets(net,inputSeries(),ta
26
27 % Setup division of data for training, Validation, Testing
28 net.divideParam.trainRatio = 70/100;
29 net.divideParam.valRatio = 15/100;
30 net.divideParam.testRatio = 15/100;
31
32 % Train the Network
33 [net,tr] = train(net,inputs,targets,inputStates,layerStates);
34
35 % Test the Network
36 outputs = net(inputs,inputStates,layerStates);
37 errors = subtract(targets,outputs);
38 performance = perform(net,targets,outputs);
39
script [Ln 1 Col 1]

```

The Train Network panel of the Neural Network Time Series Tool introduces four new plots, which you can also access from the Network Training Tool and the command line.


The error histogram of any static or dynamic network can be plotted.

`plotresponse(errors)`




The dynamic response can be plotted, with colors indicating how targets were assigned to training, validation and test sets across timesteps. (Dividing data by timesteps and other criteria, in addition to by sample, is a new feature described in “New Time Series Validation” on page 20-7.)


`plotresponse(targets, outputs)`



The autocorrelation of error across varying lag times can be plotted.
`ploterrcorr(errors)`




The input-to-error correlation can also be plotted for varying lags.
`plotinerrcorr(inputs, errors)`



Simpler time series neural network creation is provided for NARX and time-delay networks, and a new function creates NAR networks. All the network diagrams shown here are generated with the command `view(net)`.

```
net = narxnet(inputDelays, feedbackDelays, hiddenSizes,
feedbackMode, trainingFcn)
```

```
net = narnet(feedbackDelays, hiddenSizes, feedbackMode,
trainingFcn)
net = timedelaynet(inputDelays, hiddenSizes, trainingFcn)
```



Several new data sets provide sample problems that can be solved with these networks. These data sets are also available within the `ntstool` GUI and the command line.


```
[x, t] = simpleseries_dataset;
[x, t] = simplenarx_dataset;
[x, t] = exchanger_dataset;
[x, t] = maglev_dataset;
[x, t] = ph_dataset;
[x, t] = pollution_dataset;
[x, t] = refmodel_dataset;
[x, t] = robotarm_dataset;
[x, t] = valve_dataset;
```

The `preperts` function formats input and target time series for time series networks, by shifting the inputs and targets as needed to fill initial input and layer delay states. This function simplifies what is normally a tricky data preparation step that must be customized for details of each kind of network and its number of delays.

```
[x, t] = simplenarx_dataset;
net = narxnet(1:2, 1:2, 10);
[xs, xi, ai, ts] = preperts(net, x, {}, t);
net = train(net, xs, ts, xi, ai);
y = net(xs, xi, ai)
```

The output-to-input feedback of NARX and NAR networks (or custom time series network with output-to-input feedback loops) can be converted between open- and closed-loop modes using the two new functions `closeloop` and `openloop`.


```
net = narxnet(1:2, 1:2, 10);
net = closeloop(net)
net = openloop(net)
```



The total delay through a network can be adjusted with the two new functions `removedelay` and `adddelay`. Removing a delay from a NARX network which has a minimum input and feedback delay

of 1, so that it now has a minimum delay of 0, allows the network to predict the next target value a timestep ahead of when that value is expected.

```
net = removedelay(net)
net = adddelay(net)
```



The new function `catsamples` allows you to combine multiple time series into a single neural network data variable. This is useful for creating input and target data from multiple input and target time series.

```
x = catsamples(x1, x2, x3);
t = catsamples(t1, t2, t3);
```

In the case where the time series are not the same length, the shorter time series can be padded with NaN values. This will indicate “don't care” or equivalently “don't know” input and targets, and will have no effect during simulation and training.

```
x = catsamples(x1, x2, x3, 'pad')
t = catsamples(t1, t2, t3, 'pad')
```

Alternatively, the shorter series can be padded with any other value, such as zero.

```
x = catsamples(x1, x2, x3, 'pad', 0)
```

There are many other new and updated functions for handling neural network data, which make it easier to manipulate neural network time series data.

```
help nndatafun
```

New Time Series Validation

Normally during training, a data set's targets are divided up by sample into training, validation and test sets. This allows the validation set to stop training at a point of optimal generalization, and the test set to provide an independent measure of the network's accuracy. This mode of dividing up data is now indicated with a new property:

```
net.divideMode = 'sample'
```

However, many time series problems involve only a single time series. In order to support validation you can set the new property to divide data up by timestep. This is the default setting for NARXNET and other time series networks.

```
net.divideMode = 'time'
```

This property can be set manually, and can be used to specify dividing up of targets across both sample and timestep, by all target values (i.e., across sample, timestep, and output element), or not to perform data division at all.

```
net.divideMode = 'samptime'  
net.divideMode = 'all'  
net.divideMode = 'none'
```

New Time Series Properties

Time series feedback can also be controlled manually with new network properties that represent output-to-input feedback in open- or closed-loop modes. For open-loop feedback from an output from layer *i* back to input *j*, set these properties as follows:

```
net.inputs{j}.feedbackOutput = i  
net.outputs{i}.feedbackInput = j  
net.outputs{i}.feedbackMode = 'open'
```

When the feedback mode of the output is set to 'closed', the properties change to reflect that the output-to-input feedback is now implemented with internal feedback by removing input *j* from the network, and having output properties as follows:

```
net.outputs{i}.feedbackInput = [];  
net.outputs{i}.feedbackMode = 'closed'
```

Another output property keeps track of the proper closed-loop delay, when a network is in open-loop mode. Normally this property has this setting:

```
net.outputs{i}.feedbackDelay = 0
```

However, if a delay is removed from the network, it is updated to 1, to indicate that the network's output is actually one timestep ahead of its inputs, and must be delayed by 1 if it is to be converted to closed-loop form.

```
net.outputs{i}.feedbackDelay = 1
```

New Flexible Error Weighting and Performance

Performance functions have a new argument list that supports error weights for indicating which target values are more important than others. The `train` function also supports error weights.

```
net = train(net, x, t, xi, ai, ew)  
perf = mse(net, x, t, ew)
```

You can define error weights by sample, output element, time step, or network output:

```
ew = [1.0 0.5 0.7 0.2];      % Weighting errors across 4 samples  
ew = [0.1; 0.5; 1.0];      % ... across 3 output elements  
ew = {0.1 0.2 0.3 0.5 1.0}; % ... across 5 timesteps  
ew = {1.0; 0.5};          % ... across 2 network outputs
```

These can also be defined across any combination. For example, weighting error across two time series (i.e., two samples) over four timesteps:

```
ew = {[0.5 0.4], [0.3 0.5], [1.0 1.0], [0.7 0.5]};
```

In the general case, error weights can have exactly the same dimension as targets, where each target has an associated error weight.

Some performance functions are now obsolete, as their functionality has been implemented as options within the four remaining performance functions: `mse`, `mae`, `sse`, and `sae`.

The regularization implemented in `msereg` and `msnereg` is now implemented with a performance property supported by all four remaining performance functions.

```
% Any value between the default 0 and 1.  
net.performParam.regularization
```

The error normalization implemented in `msne` and `msnereg` is now implemented with a normalization property.

```
% Either 'normalized', 'percent', or the default 'none'.  
net.performParam.normalization
```

A third performance parameter indicates whether error weighting is applied to square errors (the default for `mse` and `sse`) or the absolute errors (`mae` and `sae`).


```
net.performParam.squaredWeighting % true or false
```

Compatibility Considerations

The old performance functions and old performance arguments lists continue to work as before, but are no longer recommended.

New Real Time Workshop and Improved Simulink Support

Neural network Simulink blocks now compile with Real Time Workshop® and are compatible with Rapid Accelerator mode.



`gensim` has new options for generating neural network systems in Simulink.

Name - the system name

SampleTime - the sample time


InputMode - either port, workspace, constant, or none.

OutputMode - either display, port, workspace, scope, or none

SolverMode - either default or discrete

For instance, here a NARX network is created and set up in MATLAB to use workspace inputs and outputs.

```
[x, t] = simplenarx_dataset;
net = narxnet(1:2, 1:2, 10);
[xs, xi, ai, ts] = preparets(net, x, {}, t);
net = train(net, xs, ts, xi, ai);
net = closeloop(net);
[sysName, netName] = gensim(net, 'InputMode', 'workspace', ...
    'OutputMode', 'workspace', 'SolverMode', 'discrete');
```



Simulink neural network blocks now allow initial conditions for input and layer delays to be set directly by double-clicking the neural network block. `setsiminit` and `getsiminit` provide command-line control for setting and getting input and layer delays for a neural network Simulink block.

```
setsiminit(sysName, netName, net, xi, ai);
```

New Documentation Organization and Hyperlinks

The User's Guide has been rearranged to better focus on the workflow of practical applications. The Getting Started section has been expanded.

References to functions throughout the online documentation and command-line help now link directly to their function pages.

```
help feedforwardnet
```

The command-line output of neural network objects now contains hyperlinks to documentation. For instance, here a feed-forward network is created and displayed. Its command-line output contains links to network properties, function reference pages, and parameter information.

```
net = feedforwardnet(10);
```

Subobjects of the network, such as inputs, layers, outputs, biases, weights, and parameter lists also display with links.

```
net.inputs{1}
net.layers{1}
net.outputs{2}
net.biases{1}
net.inputWeights{1, 1}
net.trainParam
```

The training tool `nntraintool` and the wizard GUIs `nftool`, `nprtool`, `nctool`, and `ntstool`, provide numerous hyperlinks to documentation.

New Derivative Functions and Property

New functions give convenient access to error gradient (of performance with respect to weights and biases) and Jacobian (of error with respect to weights and biases) calculated by various means.

```
staticderiv - Backpropagation for static networks
bttdderiv - Backpropagation through time
fpderiv - Forward propagation
num2deriv - Two-point numerical approximation
num5deriv - Five-point numerical approximation
defaultderiv - Chooses recommended derivative function for the network
```

For instance, here you can calculate the error gradient for a newly created and configured feedforward network.

```
net = feedforwardnet(10);
[x, t] = simplefit_dataset;
net = configure(net, x, t);
d = staticderiv('dperf_dwb', net, x, t)
```

Improved Network Creation

New network creation functions have clearer names, no longer need example data, and have argument lists reduced to only the arguments recommended for most applications. All arguments have defaults, so you can create simple networks by calling network functions without any arguments. New networks are also more memory efficient, as they no longer need to store sample input and target data for proper configuration of input and output processing settings.

```
% New function
net = feedforwardnet(hiddenSizes, trainingFcn)

% Old function
net = newff(x,t,hiddenSizes, transferFcns, trainingFcn, ...
           learningFcn, performanceFcn, inputProcessingFcns, ...
           outputProcessingFcns, dataDivisionFcn)
```

The new functions (and the old functions they replace) are:

```
feedforwardnet (newff)
cascadeforwardnet (newcf)
competlayer (newc)
distdelaynet (newdtdnn)
elmannet (newelm)
fitnet (newfit)
layrecnet (newlrn)
linearlayer (newlin)
lvqnet (newlvq)
narxnet (newnarx, newnarxsp)
patternnet (newpr)
perceptron (newp)
selforgmap (newsom)
```

```
timedelaynet (newtdnn)
```

The network's inputs and outputs are created with size zero, then configured for data when `train` is called or by optionally calling the new function `configure`.

```
net = configure(net, x, t)
```

Unconfigured networks can be saved and reused by configuring them for many different problems. `unconfigure` sets a configured network's inputs and outputs to zero, in a network which can later be configured for other data.

```
net = unconfigure(net)
```

Compatibility Considerations

Old functions continue working as before, but are no longer recommended.

Improved GUIs

The neural fitting `nftool`, pattern recognition `nprtool`, and clustering `nctool` GUIs have been updated with links back to the `nstart` GUI. They give the option of generating either simple or advanced scripts in their last panel. They also confirm with you when closing, if a script has not been generated, or the results not yet saved.

Improved Memory Efficiency

Memory reduction, the technique of splitting calculations up in time to reduce memory requirements, has been implemented across all training algorithms for both gradient and network simulation calculations. Previously it was only supported for gradient calculations with `trainlm` and `trainbr`.

To set the memory reduction level, use this new property. The default is 1, for no memory reduction. Setting it to 2 or higher splits the calculations into that many parts.

```
net. efficiency. memoryReduction
```

Compatibility Considerations

The `trainlm` and `trainbr` training parameter `MEM_REDUCE` is now obsolete. References to it will need to be updated. Code referring to it will generate a warning.

Improved Data Sets

All data sets in the toolbox now have help, including example solutions, and can be accessed as functions:

```
help simplefit_dataset  
[x, t] = simplefit_dataset;
```

See help for a full list of sample data sets:

```
help nndatasets
```

Updated Argument Lists

The argument lists for the following types of functions, which are not generally called directly, have been updated.

The argument list for training functions, such as `trainlm`, `traingd`, etc., have been updated to match `train`. The argument list for the adapt function `adaptwb` has been updated. The argument list for the layer and network initialization functions, `initlay`, `initnw`, and `initwb` have been updated.

Compatibility Considerations

Any custom functions of these types, or code which calls these functions manually, will need to be updated.

R2010a

Version: 6.0.4

Bug Fixes

R2009b

Version: 6.0.3

Bug Fixes

R2009a

Version: 6.0.2

Bug Fixes

R2008b

Version: 6.0.1

Bug Fixes

R2008a

Version: 6.0

New Features

Bug Fixes

Compatibility Considerations

New Training GUI with Animated Plotting Functions

Training networks with the `train` function now automatically opens a window that shows the network diagram, training algorithm names, and training status information.

The window also includes buttons for plots associated with the network being trained. These buttons launch the plots during or after training. If the plots are open during training, they update every epoch, resulting in animations that make understanding network performance much easier.

The training window can be opened and closed at the command line as follows:

```
nntraintool
nntraintool('close')
```

Two plotting functions associated with the most networks are:

- `plotperform`—Plot performance.
- `plottrainstate`—Plot training state.

Compatibility Considerations

To turn off the new training window and display command-line output (which was the default display in previous versions), use these two training parameters:

```
net.trainParam.showWindow = false;
net.trainParam.showCommandLine = true;
```

New Pattern Recognition Network, Plotting, and Analysis GUI

The `nprtool` function opens a GUI wizard that guides you to a neural network solution for pattern recognition problems. Users can define their own problems or use one of the new data sets provided.

The `newpr` function creates a pattern recognition network at the command line. Pattern recognition networks are feed-forward networks that solve problems with Boolean or 1-of- N targets and have confusion (`plotconfusion`) and receiver operating characteristic (`plotroc`) plots associated with them.

The new `confusion` function calculates the true/false, positive/negative results from comparing network output classification with target classes.

New Clustering Training, Initialization, and Plotting GUI

The `nctool` function opens a GUI wizard that guides you to a self-organizing map solution for clustering problems. Users can define their own problem or use one of the new data sets provided.

The `initsompc` function initializes the weights of self-organizing map layers to accelerate training. The `learnsomb` function implements batch training of SOMs that is orders of magnitude faster than incremental training. The `newsom` function now creates a SOM network using these faster algorithms.

Several new plotting functions are associated with self-organizing maps:

- `plotsomhits`—Plot self-organizing map input hits.

-
- `plotsomnc`—Plot self-organizing map neighbor connections.
 - `plotsomnd`—Plot self-organizing map neighbor distances.
 - `plotsomplanes`—Plot self-organizing map input weight planes.
 - `plotsompos`—Plot self-organizing map weight positions.
 - `plotsomtop`—Plot self-organizing map topology.

Compatibility Considerations

You can call the `newsom` function using conventions from earlier versions of the toolbox, but using its new calling conventions gives you faster results.

New Network Diagram Viewer and Improved Diagram Look

The new neural network diagrams support arbitrarily connected network architectures and have an improved layout. Their visual clarity has been improved with color and shading.

Network diagrams appear in all the Neural Network Toolbox graphical interfaces. In addition, you can open a network diagram viewer of any network from the command line by typing

```
view(net)
```

New Fitting Network, Plots and Updated Fitting GUI

The `newfit` function creates a fitting network that consists of a feed-forward backpropagation network with the fitting plot (`plotfit`) associated with it.

The `nftool` wizard has been updated to use `newfit`, for simpler operation, to include the new network diagrams, and to include sample data sets. It now allows a Simulink block version of the trained network to be generated from the final results panel.

Compatibility Considerations

The code generated by `nftool` is different the code generated in previous versions. However, the code generated by earlier versions still operates correctly.

R2007b

Version: 5.1

New Features

Bug Fixes

Compatibility Considerations

Simplified Syntax for Network-Creation Functions

The following network-creation functions have new input arguments to simplify the network creation process:

- `newcf`
- `newff`
- `newtdnn`
- `newelm`
- `newfftd`
- `newlin`
- `newlrn`
- `newnarx`
- `newnarxsp`

For detailed information about each function, see the corresponding reference pages.

Changes to the syntax of network-creation functions have the following benefits:

- You can now specify input and target data values directly. In the previous release, you specified input ranges and the size of the output layer instead.
- The new syntax automates preprocessing, data division, and postprocessing of data.

For example, to create a two-layer feed-forward network with 20 neurons in its hidden layer for a given a matrix of input vectors `p` and target vectors `t`, you can now use `newff` with the following arguments:

```
net = newff(p,t,20);
```

This command also sets properties of the network such that the functions `sim` and `train` automatically preprocess inputs and targets, and postprocess outputs.

In the previous release, you had to use the following three commands to create the same network:

```
pr = minmax(p);  
s2 = size(t,1);  
net = newff(pr,[20 s2]);
```

Compatibility Considerations

Your existing code still works but might produce a warning that you are using obsolete syntax.

Automated Data Preprocessing and Postprocessing During Network Creation

Automated data preprocessing and postprocessing occur during network creation in the Network/Data Manager GUI (`nntool`), Neural Network Fitting Tool GUI (`nftool`), and at the command line.

At the command line, the new syntax for using network-creation functions, automates preprocessing, postprocessing, and data-division operations.

For example, the following code returns a network that automatically preprocesses the inputs and targets and postprocesses the outputs:

```
net = newff(p,t,20);  
net = train(net,p,t);  
y = sim(net,p);
```

To create the same network in a previous release, you used the following longer code:

```
[p1,ps1] = removeconstantrows(p);  
[p2,ps2] = mapminmax(p1);  
[t1,ts1] = mapminmax(t);  
pr = minmax(p2);  
s2 = size(t1,1);  
net = newff(pr,[20 s2]);  
net = train(net,p2,t1);  
y1 = sim(net,p2);  
y = mapminmax('reverse',y1,ts1);
```

Default Processing Settings

The default input `processFcns` functions returned with a new network are, as follows:

```
net.inputs{1}.processFcns = ...  
    {'fixunknowns','removeconstantrows','mapminmax'}
```

These three processing functions perform the following operations, respectively:

- `fixunknowns`—Encode unknown or missing values (represented by NaN) using numerical values that the network can accept.
- `removeconstantrows`—Remove rows that have constant values across all samples.
- `mapminmax`—Map the minimum and maximum values of each row to the interval [-1 1].

The elements of `processParams` are set to the default values of the `fixunknowns`, `removeconstantrows`, and `mapminmax` functions.

The default output `processFcns` functions returned with a new network include the following:

```
net.outputs{2}.processFcns = {'removeconstantrows','mapminmax'}
```

These defaults process outputs by removing rows with constant values across all samples and mapping the values to the interval [-1 1].

`sim` and `train` automatically process inputs and targets using the input and output processing functions, respectively. `sim` and `train` also reverse-process network outputs as specified by the output processing functions.

For more information about processing input, target, and output data, see “Multilayer Networks and Backpropagation Training” in the Neural Network Toolbox User's Guide.

Changing Default Input Processing Functions

You can change the default processing functions either by specifying optional processing function arguments with the network-creation function, or by changing the value of `processFcns` after creating your network.

You can also modify the default parameters for each processing function by changing the elements of the `processParams` properties.

After you create a network object (`net`), you can use the following input properties to view and modify the automatic processing settings:

- `net.inputs{1}.exampleInput`—Matrix of example input vectors
- `net.inputs{1}.processFcns`—Cell array of processing function names
- `net.inputs{1}.processParams`—Cell array of processing parameters

The following input properties are automatically set and you cannot change them:

- `net.inputs{1}.processSettings`—Cell array of processing settings
- `net.inputs{1}.processedRange`—Ranges of example input vectors after processing
- `net.inputs{1}.processedSize`—Number of input elements after processing

Changing Default Output Processing Functions

After you create a network object (`net`), you can use the following output properties to view and modify the automatic processing settings:

- `net.outputs{2}.exampleOutput`—Matrix of example output vectors
- `net.outputs{2}.processFcns`—Cell array of processing function names
- `net.outputs{2}.processParams`—Cell array of processing parameters

Note These output properties require a network that has the output layer as the second layer.

The following new output properties are automatically set and you cannot change them:

- `net.outputs{2}.processSettings`—Cell array of processing settings
- `net.outputs{2}.processedRange`—Ranges of example output vectors after processing
- `net.outputs{2}.processedSize`—Number of input elements after processing

Automated Data Division During Network Creation

When training with supervised training functions, such as the Levenberg-Marquardt backpropagation (the default for feed-forward networks), you can supply three sets of input and target data. The first data set trains the network, the second data set stops training when generalization begins to suffer, and the third data set provides an independent measure of network performance.

Automated data division occurs during network creation in the Network/Data Manager GUI, Neural Network Fitting Tool GUI, and at the command line.

At the command line, to create and train a network with early stopping that uses 20% of samples for validation and 20% for testing, you can use the following code:

```
net = newff(p,t,20);  
net = train(net,p,t);
```

Previously, you entered the following code to accomplish the same result:

```
pr = minmax(p);
s2 = size(t,1);
net = newff(pr,[20 s2]);
[trainV,validateV,testV] = dividevec(p,t,0.2,0.2);
[net,tr] = train(net,trainV.P,trainV.T,[],[],validateV,testV);
```

For more information about data division, see “Multilayer Networks and Backpropagation Training” in the Neural Network Toolbox User's Guide.

New Data Division Functions

The following are new data division functions:

- `dividerand`—Divide vectors using random indices.
- `divideblock`—Divide vectors in three blocks of indices.
- `divideint`—Divide vectors with interleaved indices.
- `divideind`—Divide vectors according to supplied indices.

Default Data Division Settings

Network creation functions return the following default data division properties:

- `net.divideFcn = 'dividerand'`
- `net.divideParam.trainRatio = 0.6;`
- `net.divideParam.valRatio = 0.2;`
- `net.divideParam.testRatio = 0.2;`

Calling `train` on the network object `net` divided the set of input and target vectors into three sets, such that 60% of the vectors are used for training, 20% for validation, and 20% for independent testing.

Changing Default Data Division Settings

You can override default data division settings by either supplying the optional data division argument for a network-creation function, or by changing the corresponding property values after creating the network.

After creating a network, you can view and modify the data division behavior using the following new network properties:

- `net.divideFcn`—Name of the division function
- `net.divideParam`—Parameters for the division function

New Simulink Blocks for Data Preprocessing

New blocks for data processing and reverse processing are available. For more information, see “Processing Blocks” in the Neural Network Toolbox User's Guide.

The function `gensim` now generates neural networks in Simulink that use the new processing blocks.

Properties for Targets Now Defined by Properties for Outputs

The properties for targets are now defined by the properties for outputs. Use the following properties to get and set the output and target properties of your network:

- `net.numOutputs`—The number of outputs and targets
- `net.outputConnect`—Indicates which layers have outputs and targets
- `net.outputs`—Cell array of output subobjects defining each output and its target

Compatibility Considerations

Several properties are now obsolete, as described in the following table. Use the new properties instead.

Recommended Property	Obsolete Property
<code>net.numOutputs</code>	<code>net.numTargets</code>
<code>net.outputConnect</code>	<code>net.targetConnect</code>
<code>net.outputs</code>	<code>net.targets</code>

R2007a

Version: 5.0.2

No New Features or Changes

R2006b

Version: 5.0.1

No New Features or Changes

R2006a

Version: 5.0

New Features

Compatibility Considerations

Dynamic Neural Networks

Version 5.0 now supports these types of dynamic neural networks:

Time-Delay Neural Network

Both focused and distributed time-delay neural networks are now supported. Continue to use the `newfftd` function to create focused time-delay neural networks. To create distributed time-delay neural networks, use the `newdtdnn` function.

Nonlinear Autoregressive Network (NARX)

To create parallel NARX configurations, use the `newnarx` function. To create series-parallel NARX networks, use the `newnarxsp` function. The `sp2narx` function lets you convert NARX networks from series-parallel to parallel configuration, which is useful for training.

Layer Recurrent Network (LRN)

Use the `newlrn` function to create LRN networks. LRN networks are useful for solving some of the more difficult problems in filtering and modeling applications.

Custom Networks

The training functions in Neural Network Toolbox are enhanced to let you train arbitrary custom dynamic networks that model complex dynamic systems. For more information about working with these networks, see the Neural Network Toolbox documentation.

Wizard for Fitting Data

The new Neural Network Fitting Tool (`nftool`) is now available to fit your data using a neural network. The Neural Network Fitting Tool is designed as a wizard and walks you through the data-fitting process step by step.

To open the Neural Network Fitting Tool, type the following at the MATLAB prompt:

```
nftool
```

Data Preprocessing and Postprocessing

Version 5.0 provides the following new data preprocessing and postprocessing functionality:

`dividevec` Automatically Splits Data

The `dividevec` function facilitates dividing your data into three distinct sets to be used for training, cross validation, and testing, respectively. Previously, you had to split the data manually.

`fixunknowns` Encodes Missing Data

The `fixunknowns` function encodes missing values in your data so that they can be processed in a meaningful and consistent way during network training. To reverse this preprocessing operation and return the data to its original state, call `fixunknowns` again with `'reverse'` as the first argument.

removeconstantrows Handles Constant Values

`removeconstantrows` is a new helper function that processes matrices by removing rows with constant values.

mapminmax, mapstd, and processpca Are New

The `mapminmax`, `mapstd`, and `processpca` functions are new and perform data preprocessing and postprocessing operations.

Compatibility Considerations

Several functions are now obsolete, as described in the following table. Use the new functions instead.

New Function	Obsolete Functions
<code>mapminmax</code>	<code>premnmx</code> <code>postmnmx</code> <code>trammx</code>
<code>mapstd</code>	<code>prestd</code> <code>poststd</code> <code>trastd</code>
<code>processpca</code>	<code>prepca</code> <code>trapca</code>

Each new function is more efficient than its obsolete predecessors because it accomplishes both preprocessing and postprocessing of the data. For example, previously you used `premnmx` to process a matrix, and then `postmnmx` to return the data to its original state. In this release, you accomplish both operations using `mapminmax`; to return the data to its original state, you call `mapminmax` again with 'reverse' as the first argument:

```
mapminmax('reverse',Y,PS)
```

Derivative Functions Are Obsolete

The following derivative functions are now obsolete:

```
ddotprod  
dhardlim  
dhardlms  
dlogsig  
dmae  
dmse  
dmsereg  
dnetprod  
dnetsum  
dpostlin  
dpurelin  
dradbas  
dsatlin  
dsatlins  
dsse
```

`dtansig`
`dtribas`

Each derivative function is named by prefixing a `d` to the corresponding function name. For example, `sse` calculates the network performance function and `dsse` calculated the derivative of the network performance function.

Compatibility Considerations

To calculate a derivative in this version, you must pass a derivative argument to the function. For example, to calculate the derivative of a hyperbolic tangent sigmoid transfer function `A` with respect to `N`, use this syntax:

```
A = tansig(N,FP)
dA_dN = tansig('dn',N,A,FP)
```

Here, the argument `'dn'` requests the derivative to be calculated.

R14SP3

Version: 4.0.6

No New Features or Changes

