

Fuzzy Logic Toolbox™

User's Guide



MATLAB®

R2022a



How to Contact MathWorks



Latest news: www.mathworks.com
Sales and services: www.mathworks.com/sales_and_services
User community: www.mathworks.com/matlabcentral
Technical support: www.mathworks.com/support/contact_us



Phone: 508-647-7000



The MathWorks, Inc.
1 Apple Hill Drive
Natick, MA 01760-2098

Fuzzy Logic Toolbox™ User's Guide

© COPYRIGHT 1995–2022 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See www.mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

Patents

MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

Revision History

January 1995	First printing	
April 1997	Second printing	
January 1998	Third printing	
September 2000	Fourth printing	
April 2003	Fifth printing	
June 2004	Online only	Revised for Version 2 (Release 12)
March 2005	Online only	Updated for Version 2.1.3 (Release 14)
September 2005	Online only	Updated for Version 2.2.1 (Release 14SP2)
March 2006	Online only	Updated for Version 2.2.2 (Release 14SP3)
September 2006	Online only	Updated for Version 2.2.3 (Release 2006a)
March 2007	Online only	Updated for Version 2.2.4 (Release 2006b)
September 2007	Online only	Updated for Version 2.2.5 (Release 2007a)
March 2008	Online only	Revised for Version 2.2.6 (Release 2007b)
October 2008	Online only	Revised for Version 2.2.7 (Release 2008a)
March 2009	Online only	Revised for Version 2.2.8 (Release 2008b)
September 2009	Online only	Revised for Version 2.2.9 (Release 2009a)
March 2010	Online only	Revised for Version 2.2.10 (Release 2009b)
September 2010	Online only	Revised for Version 2.2.11 (Release 2010a)
April 2011	Online only	Revised for Version 2.2.12 (Release 2010b)
September 2011	Online only	Revised for Version 2.2.13 (Release 2011a)
March 2012	Online only	Revised for Version 2.2.14 (Release 2011b)
September 2012	Online only	Revised for Version 2.2.15 (Release 2012a)
March 2013	Online only	Revised for Version 2.2.16 (Release 2012b)
September 2013	Online only	Revised for Version 2.2.17 (Release 2013a)
March 2014	Online only	Revised for Version 2.2.18 (Release 2013b)
October 2014	Online only	Revised for Version 2.2.19 (Release 2014a)
March 2015	Online only	Revised for Version 2.2.20 (Release 2014b)
September 2015	Online only	Revised for Version 2.2.21 (Release 2015a)
March 2016	Online only	Revised for Version 2.2.22 (Release 2015b)
September 2016	Online only	Revised for Version 2.2.23 (Release 2016a)
March 2017	Online only	Revised for Version 2.2.24 (Release 2016b)
September 2017	Online only	Revised for Version 2.2.25 (Release 2017a)
March 2018	Online only	Revised for Version 2.3 (Release 2017b)
September 2018	Online only	Revised for Version 2.3.1 (Release 2018a)
March 2019	Online only	Revised for Version 2.4 (Release 2018b)
September 2019	Online only	Revised for Version 2.5 (Release 2019a)
March 2020	Online only	Revised for Version 2.6 (Release 2019b)
September 2020	Online only	Revised for Version 2.7 (Release 2020a)
March 2021	Online only	Revised for Version 2.8 (Release 2020b)
September 2021	Online only	Revised for Version 2.8.1 (Release 2021a)
March 2022	Online only	Revised for Version 2.8.2 (Release 2021b)
		Revised for Version 2.9 (Release 2022a)

Getting Started

1

Fuzzy Logic Toolbox Product Description	1-2
Key Features	1-2
What Is Fuzzy Logic?	1-3
Description of Fuzzy Logic	1-3
Why Use Fuzzy Logic?	1-5
When Not to Use Fuzzy Logic	1-6
What Can Fuzzy Logic Toolbox Software Do?	1-6
Foundations of Fuzzy Logic	1-7
Overview	1-7
Fuzzy Sets	1-7
Membership Functions	1-9
Logical Operations	1-13
If-Then Rules	1-15
References	1-17
Fuzzy Inference Process	1-19
Fuzzify Inputs	1-20
Apply Fuzzy Operator	1-20
Apply Implication Method	1-21
Aggregate All Outputs	1-22
Defuzzify	1-22
Fuzzy Inference Diagram	1-23
Defuzzification Methods	1-25
Fuzzy vs. Nonfuzzy Logic	1-30

Fuzzy Inference System Modeling

2

Mamdani and Sugeno Fuzzy Inference Systems	2-2
Mamdani Fuzzy Inference Systems	2-2
Sugeno Fuzzy Inference Systems	2-3
Type-2 Fuzzy Inference Systems	2-7
Interval Type-2 Membership Functions	2-7
Type-2 Fuzzy Inference Systems	2-7
Fuzzy Inference Process for Type-2 Fuzzy Systems	2-8
Type-Reduction Methods	2-12

Build Fuzzy Systems Using Fuzzy Logic Designer	2-14
Fuzzy Logic Toolbox Graphical User Interface Tools	2-14
The Basic Tipping Problem	2-16
Fuzzy Logic Designer	2-16
The Membership Function Editor	2-20
The Rule Editor	2-25
The Rule Viewer	2-27
The Surface Viewer	2-29
Importing and Exporting Fuzzy Inference Systems	2-30
Build Fuzzy Systems at the Command Line	2-31
Build Fuzzy Systems Using Custom Functions	2-40
Build Fuzzy Inference Systems Using Custom Functions in Fuzzy Logic Designer	2-40
Specify Custom Membership Functions	2-41
Specify Custom Inference Functions	2-45
Specify Custom Type-Reduction Functions	2-50
Use Custom Functions in Code Generation	2-50
Fuzzy Trees	2-52
Types of Hierarchical Structures	2-52
Add or Remove FIS Tree Outputs	2-56
Use the Same Value for Multiple inputs of FIS Tree	2-56
Update Fuzzy Inference Systems in FIS Tree	2-57
Tune a Fuzzy Tree	2-57
Fuzzy PID Control with Type-2 FIS	2-58
Fuzzy Logic Image Processing	2-72

Fuzzy Inference System Tuning

3

Tuning Fuzzy Inference Systems	3-2
Tuning Methods	3-3
Prevent Overfitting of Tuned System	3-4
Improve Tuning Results	3-4
Tune Fuzzy Rules and Membership Function Parameters	3-6
Tune Fuzzy Trees	3-15
Customize FIS Tuning Process	3-20
Tune Mamdani Fuzzy Inference System	3-28
Tune FIS Tree for Gas Mileage Prediction	3-38
Optimize FIS Parameters with k-Fold Cross-Validation	3-51
Predict Chaotic Time Series Using Type-2 FIS	3-58

Tune Fuzzy Robot Obstacle Avoidance System Using Custom Cost Function	3-71
Classify Pixels Using Fuzzy Systems	3-82
Autonomous Parking Using Fuzzy Inference System	3-98
Design Controller for Artificial Pancreas Using Fuzzy Logic	3-114
Explain Black-Box Model Using Fuzzy Support System	3-131
Explainable Fuzzy Support System for Black-Box Model of Robot Obstacle Avoidance	3-154
Neuro-Adaptive Learning and ANFIS	3-171
FIS Structure	3-171
Training Data	3-172
Training Options	3-172
Display Options	3-173
Training Validation	3-173
Training Results	3-174
Training Algorithm Differences	3-175
Train Adaptive Neuro-Fuzzy Inference Systems	3-177
Load Training Data	3-177
Generate or Load FIS Structure	3-179
Train FIS	3-181
Validate Trained FIS	3-182
Importance of Checking Data	3-183
Save Training Error Data to MATLAB Workspace	3-187
Predict Chaotic Time-Series Using ANFIS	3-193
Modeling Inverse Kinematics in a Robotic Arm	3-201
Adaptive Noise Cancellation Using ANFIS	3-209
Nonlinear System Identification	3-217
Gas Mileage Prediction	3-227

Data Clustering

4

Fuzzy Clustering	4-2
What Is Data Clustering?	4-2
Fuzzy C-Means Clustering	4-2
Subtractive Clustering	4-2
References	4-3

Cluster Quasi-Random Data Using Fuzzy C-Means Clustering	4-4
Adjust Fuzzy Overlap in Fuzzy C-Means Clustering	4-7
Fuzzy C-Means Clustering	4-9
Fuzzy C-Means Clustering for Iris Data	4-13
Model Suburban Commuting Using Subtractive Clustering and ANFIS	4-17
Cluster Data Using Clustering Tool	4-29
Load and Plot Data	4-29
Cluster Data	4-30
Save Cluster Centers	4-31

Fuzzy Logic in Simulink

5

Simulate Fuzzy Inference Systems in Simulink	5-2
Simulate Fuzzy Inference System	5-2
Access Intermediate Fuzzy Inference Results	5-8
Simulation Modes	5-9
Map Command-Line Functionality to Fuzzy Logic Controller Block	5-9
Water Level Control in a Tank	5-11
Temperature Control in a Shower	5-17
Implement Fuzzy PID Controller in Simulink Using Lookup Table	5-24

Deployment

6

Deploy Fuzzy Inference Systems	6-2
Generate Code in Simulink	6-2
Generate Code in MATLAB	6-2
Generate Code for Fuzzy System Using Simulink Coder	6-3
Generate Structured Text for Fuzzy System Using Simulink PLC Coder	6-7
Generate Code for Fuzzy System Using MATLAB Coder	6-10

Apps

7

Functions

8

Objects

9

Blocks

10

Getting Started

- “Fuzzy Logic Toolbox Product Description” on page 1-2
- “What Is Fuzzy Logic?” on page 1-3
- “Foundations of Fuzzy Logic” on page 1-7
- “Fuzzy Inference Process” on page 1-19
- “Defuzzification Methods” on page 1-25
- “Fuzzy vs. Nonfuzzy Logic” on page 1-30

Fuzzy Logic Toolbox Product Description

Design and simulate fuzzy logic systems

Fuzzy Logic Toolbox provides MATLAB® functions, apps, and a Simulink® block for analyzing, designing, and simulating systems based on fuzzy logic. The product guides you through the steps of designing fuzzy inference systems. Functions are provided for many common methods, including fuzzy clustering and adaptive neuro-fuzzy learning.

The toolbox lets you model complex system behaviors using simple logic rules, and then implement these rules in a fuzzy inference system. You can use it as a stand-alone fuzzy inference engine. Alternatively, you can use fuzzy inference blocks in Simulink and simulate the fuzzy systems within a comprehensive model of the entire dynamic system.

Key Features

- Fuzzy Logic Design app for building fuzzy inference systems and viewing and analyzing results
- Membership functions for creating fuzzy inference systems
- Support for AND, OR, and NOT logic in user-defined rules
- Standard Mamdani and Sugeno-type fuzzy inference systems
- Automated membership function shaping through neuroadaptive and fuzzy clustering learning techniques
- Ability to embed a fuzzy inference system in a Simulink model
- Ability to generate embeddable C code or stand-alone executable fuzzy inference engines

What Is Fuzzy Logic?

Description of Fuzzy Logic

In recent years, the number and variety of applications of fuzzy logic have increased significantly. The applications range from consumer products such as cameras, camcorders, washing machines, and microwave ovens to industrial process control, medical instrumentation, decision-support systems, and portfolio selection.

To understand why use of fuzzy logic has grown, you must first understand what is meant by fuzzy logic.

Fuzzy logic has two different meanings. In a narrow sense, fuzzy logic is a logical system, which is an extension of multivalued logic. However, in a wider sense fuzzy logic (FL) is almost synonymous with the theory of fuzzy sets, a theory which relates to classes of objects without crisp, clearly defined boundaries. In such cases, membership in a set is a matter of degree. In this perspective, fuzzy logic in its narrow sense is a branch of FL. Even in its more narrow definition, fuzzy logic differs both in concept and substance from traditional multivalued logical systems.


In Fuzzy Logic Toolbox software, fuzzy logic should be interpreted as FL, that is, fuzzy logic in its wide sense. The basic ideas underlying FL are explained in "Foundations of Fuzzy Logic" on page 1-7. What might be added is that the basic concept underlying FL is that of a linguistic variable, that is, a variable whose values are words rather than numbers. In effect, much of FL may be viewed as a methodology for computing with words rather than numbers. Although words are inherently less precise than numbers, their use is closer to human intuition. Furthermore, computing with words exploits the tolerance for imprecision and thereby lowers the cost of solution.

Another basic concept in FL, which plays a central role in most of its applications, is that of a fuzzy if-then rule or, simply, fuzzy rule. Although rule-based systems have a long history of use in Artificial Intelligence (AI), what is missing in such systems is a mechanism for dealing with fuzzy consequents and fuzzy antecedents. In fuzzy logic, this mechanism is provided by the calculus of fuzzy rules. The calculus of fuzzy rules serves as a basis for what might be called the Fuzzy Dependency and Command Language (FDCL). Although FDCL is not used explicitly in the toolbox, it is effectively one of its principal constituents. In most of the applications of fuzzy logic, a fuzzy logic solution is, in reality, a translation of a human solution into FDCL.

A trend that is growing in visibility relates to the use of fuzzy logic in combination with neurocomputing and genetic algorithms. More generally, fuzzy logic, neurocomputing, and genetic algorithms may be viewed as the principal constituents of what might be called soft computing. Unlike the traditional, hard computing, *soft computing* accommodates the imprecision of the real world. The guiding principle of soft computing is: Exploit the tolerance for imprecision, uncertainty, and partial truth to achieve tractability, robustness, and low solution cost. In the future, soft computing could play an increasingly important role in the conception and design of systems whose MIQ (Machine IQ) is much higher than that of systems designed by conventional methods.

Among various combinations of methodologies in soft computing, the one that has highest visibility at this juncture is that of fuzzy logic and neurocomputing, leading to neuro-fuzzy systems. Within fuzzy logic, such systems play a particularly important role in the induction of rules from observations. An effective method developed by Dr. Roger Jang for this purpose is called ANFIS (Adaptive Neuro-Fuzzy Inference System). This method is an important component of the toolbox.


Fuzzy logic approximates human reasoning and does a good job of balancing the tradeoff between precision and significance. For instance, when warning someone of an object falling toward them, being precise about the exact mass and speed is not necessary.



Fuzzy logic is a convenient way to map an input space to an output space. Consider the following examples.

- With information about how good your service was at a restaurant, a fuzzy logic system can tell you what the tip should be.
- With your specification of how hot you want the water, a fuzzy logic system can adjust the faucet valve to the right setting.
- With information about how far away the subject of your photograph is, a fuzzy logic system can focus the lens for you.
- With information about how fast the car is going and how hard the motor is working, a fuzzy logic system can shift gears for you.

A fuzzy system behaves like a black box that maps an input space to an output space. For example, you can map the input space of all possible restaurant service ratings to all possible tip values.



An input/output map for the tipping problem:
"Given the quality of service, how much should I tip?"

Determining the appropriate amount of tip requires mapping inputs to the appropriate outputs. Between the input and the output, the preceding figure shows a black box that can contain any number of things: fuzzy systems, linear systems, expert systems, neural networks, differential equations, interpolated multidimensional lookup tables, or even a spiritual advisor, just to name a few of the possible options. Clearly the list could go on and on.

Of the dozens of ways to make the black box work, it turns out that fuzzy is often the very best way. Why should that be? As Lotfi Zadeh, who is considered to be the father of fuzzy logic, once remarked: "In almost every case you can build the same product without fuzzy logic, but fuzzy is faster and cheaper."

Why Use Fuzzy Logic?

Here is a list of general observations about fuzzy logic:

- Fuzzy logic is conceptually easy to understand.

The mathematical concepts behind fuzzy reasoning are very simple. Fuzzy logic is a more intuitive approach without the far-reaching complexity.

- Fuzzy logic is flexible.

With any given system, it is easy to layer on more functionality without starting again from scratch.

- Fuzzy logic is tolerant of imprecise data.

Everything is imprecise if you look closely enough, but more than that, most things are imprecise even on careful inspection. Fuzzy reasoning builds this understanding into the process rather than tacking it onto the end.

- Fuzzy logic can model nonlinear functions of arbitrary complexity.

You can create a fuzzy system to match any set of input-output data. This process is made particularly easy by adaptive techniques like Adaptive Neuro-Fuzzy Inference Systems (ANFIS), which are available in Fuzzy Logic Toolbox software.

- Fuzzy logic can be built on top of the experience of experts.

In direct contrast to neural networks, which take training data and generate opaque, impenetrable models, fuzzy logic lets you rely on the experience of people who already understand your system.

- Fuzzy logic can be blended with conventional control techniques.

Fuzzy systems don't necessarily replace conventional control methods. In many cases fuzzy systems augment them and simplify their implementation.

- Fuzzy logic is based on natural language.

The basis for fuzzy logic is the basis for human communication. This observation underpins many of the other statements about fuzzy logic. Because fuzzy logic is built on the structures of qualitative description used in everyday language, fuzzy logic is easy to use.

The last statement is perhaps the most important one and deserves more discussion. Natural language, which is used by ordinary people on a daily basis, has been shaped by thousands of years of human history to be convenient and efficient. Sentences written in ordinary language represent a triumph of efficient communication.

When Not to Use Fuzzy Logic

Fuzzy logic is not a cure-all. When should you not use fuzzy logic? The safest statement is the first one made in this introduction: fuzzy logic is a convenient way to map an input space to an output space. If you find it's not convenient, try something else. If a simpler solution already exists, use it. Fuzzy logic is the codification of common sense — use common sense when you implement it and you will probably make the right decision. Many controllers, for example, do a fine job without using fuzzy logic. However, if you take the time to become familiar with fuzzy logic, you'll see it can be a very powerful tool for dealing quickly and efficiently with imprecision and nonlinearity.

What Can Fuzzy Logic Toolbox Software Do?

Using Fuzzy Logic Toolbox software, you can:

- Create and edit fuzzy inference systems using command-line functions or the **Fuzzy Logic Designer** app.
- Automatically generate fuzzy systems using clustering or adaptive neuro-fuzzy techniques.
- Automatically tune the parameters of a fuzzy logic system using optimization methods such as genetic algorithms and particle swarm optimization. For more information, see “Tuning Fuzzy Inference Systems” on page 3-2.
- Simulate your fuzzy system within a Simulink model using the Fuzzy Logic Controller block.
- Automatically generate code for evaluating fuzzy inference systems. For more information, see “Deploy Fuzzy Inference Systems” on page 6-2.

See Also

More About

- “Foundations of Fuzzy Logic” on page 1-7
- “Fuzzy vs. Nonfuzzy Logic” on page 1-30

Foundations of Fuzzy Logic

Overview

The point of fuzzy logic is to map an input space to an output space, and the primary mechanism for doing this is a list of if-then statements called rules. All rules are evaluated in parallel, and the order of the rules is unimportant. The rules themselves are useful because they refer to variables and the adjectives that describe those variables. Before you can build a system that interprets rules, you must define all the terms you plan on using and the adjectives that describe them. To say that the water is hot, you need to define the range within which the water temperature can be expected to vary as well as what you mean by the word *hot*.


In general, fuzzy inference is a method that interprets the values in the input vector and, based on some set of rules, assigns values to the output vector.

This topic guides you through the fuzzy logic process step-by-step by providing an introduction to the theory and practice of fuzzy logic.

Fuzzy Sets

Fuzzy logic starts with the concept of a fuzzy set. A fuzzy set is a set without a crisp, clearly defined boundary. It can contain elements with only a partial degree of membership.

To understand what a fuzzy set is, first consider the definition of a *classical set*. A classical set is a container that wholly includes or wholly excludes any given element. For example, the set of days of the week unquestionably includes Monday, Thursday, and Saturday. It just as unquestionably excludes butter, liberty, and dorsal fins, and so on.



This type of set is called a classical set because it has been around for a long time. It was Aristotle who first formulated the Law of the Excluded Middle, which says X must either be in set A or in set not-A. Another version of this law is:


Of any subject, one thing must be either asserted or denied.

To restate this law with annotations: "Of any subject (say Monday), one thing (a day of the week) must be either asserted or denied (I assert that Monday is a day of the week)." This law demands that opposites, the two categories A and not-A, should between them contain the entire universe. Everything falls into either one group or the other. There is no thing that is both a day of the week and not a day of the week.

Now, consider the set of days comprising a weekend. The following diagram attempts to classify the weekend days.

Most would agree that Saturday and Sunday belong in the weekend set, but what about Friday? It feels like a part of the weekend, but somehow it seems like it should be technically excluded.

Therefore, Friday "straddles the fence." Classical sets do not tolerate this kind of classification. Either something is in a set or it is out of a set. Human experience suggests something different, however, straddling the fence is part of life.



Of course, individual perceptions and cultural background must be taken into account when you define what constitutes the weekend. Even the dictionary is imprecise, defining the weekend as the period from Friday night or Saturday to Monday morning. You are entering the realm where sharp-edged, yes-no logic stops being helpful. Fuzzy reasoning becomes valuable exactly when you work with how people really perceive the concept *weekend* as opposed to a simple-minded classification useful for accounting purposes only. More than anything else, the following statement lays the foundations for fuzzy logic.


In fuzzy logic, the truth of any statement becomes a matter of degree.

Any statement can be fuzzy. The major advantage that fuzzy reasoning offers is the ability to reply to a yes-no question with a not-quite-yes-or-no answer. Humans do this kind of thing all the time (think how rarely you get a straight answer to a seemingly simple question), but it is a rather new trick for computers.

How does it work? Reasoning in fuzzy logic is just a matter of generalizing the familiar yes-no (Boolean) logic. If you give true the numerical value of 1 and false the numerical value of 0, this value indicates that fuzzy logic also permits in-between values like 0.2 and 0.7453. For instance:


- Q: Is Saturday a weekend day?
- A: 1 (yes, or true)
- Q: Is Tuesday a weekend day?
- A: 0 (no, or false)
- Q: Is Friday a weekend day?
- A: 0.8 (for the most part yes, but not completely)
- Q: Is Sunday a weekend day?
- A: 0.95 (yes, but not quite as much as Saturday).

The plot on the left shows the truth values for weekend-ness if you are forced to respond with an absolute yes or no response. On the right is a plot that shows the truth value for weekend-ness if you are allowed to respond with fuzzy in-between values.



Technically, the representation on the right is from the domain of *multivalued logic* (or multivalent logic). If you ask the question "Is X a member of set A?" the answer might be yes, no, or any one of a thousand intermediate values in between. Thus, X might have partial membership in A. Multivalued logic stands in direct contrast to the more familiar concept of two-valued (or bivalent yes-no) logic.


To return to the example, now consider a continuous scale time plot of weekend-ness shown in the following plots.



By making the plot continuous, you are defining the degree to which any given instant belongs in the weekend rather than an entire day. In the plot on the left, notice that at midnight on Friday, just as the second hand sweeps past 12, the weekend-ness truth value jumps discontinuously from 0 to 1. This is one way to define the weekend, and while it may be useful to an accountant, it may not really connect with your own real-world experience of weekend-ness.

The plot on the right shows a smoothly varying curve that accounts for the fact that all of Friday, and, to a small degree, parts of Thursday, partake of the quality of weekend-ness and thus deserve partial membership in the fuzzy set of weekend moments. The curve that defines the weekend-ness of any instant in time is a function that maps the input space (time of the week) to the output space (weekend-ness). Specifically, it is known as a *membership function*. See "Membership Functions" on page 1-9 for a more detailed discussion.


As another example of fuzzy sets, consider the question of seasons. What season is it right now? In the northern hemisphere, summer officially begins at the exact moment in the earth's orbit when the North Pole is pointed most directly toward the sun. It occurs exactly once a year, in late June. Using the astronomical definitions for the season, you get sharp boundaries as shown on the left in the figure that follows. But what you experience as the seasons vary more or less continuously as shown on the right in the following figure (in temperate northern hemisphere climates).




Membership Functions

A *membership function* (MF) is a curve that defines how each point in the input space is mapped to a membership value (or degree of membership) between 0 and 1. The input space is often referred to as the *universe of discourse*.

One of the most commonly used examples of a fuzzy set is the set of tall people. In this case, the universe of discourse is all potential heights, say from three feet to nine feet. The word *tall* corresponds to a curve that defines the degree to which any person is tall. If the set of tall people is given the well-defined (crisp) boundary of a classical set, you might say all people taller than six feet are officially considered tall. However, it is unreasonable to call one person short and another one tall when they differ in height by an inch.



If the kind of distinction shown previously is unworkable, then what is the right way to define the set of tall people? Much as with the plot of weekend days, the following figure shows a smoothly varying curve that passes from not-tall to tall. The output axis is a number known as the membership value between 0 and 1. The curve is known as a *membership function* and is often given the designation of μ . For example, the following figure shows both crisp and smooth tall membership functions. In the top plot, the two people are classified as either entirely tall or entirely not-tall. In the bottom plot, the smooth transition allows for different degrees of tallness. Both people are tall to some degree, but one is significantly less tall than the other. The taller person, with a tallness membership of 0.95 is definitely a tall person, but the person with a tallness membership of 0.3 is not very tall.



Subjective interpretations and appropriate units are built into fuzzy sets. If you say "She's tall," then the *tall* membership function should already take into account whether you are referring to a six-year-old or a grown woman. Similarly, the units are included in the curve since it makes no sense to say "Is she tall in inches or in meters?"

Membership Functions in Fuzzy Logic Toolbox Software

The only condition a membership function must satisfy is that its membership values must vary between 0 and 1. The function itself can be an arbitrary optimized for your desired combination of simplicity, convenience, speed, and efficiency.

A classical set might be expressed as:

$$A = \{x | x > 6\}$$

A fuzzy set is an extension of a classical set. If X is the universe of discourse and its elements are denoted by x , then a fuzzy set A in X is defined as a set of ordered pairs.

$$A\{x, \mu_A(x) | x \in X\}$$


$\mu_A(x)$ is called the membership function (or MF) of x in A . The membership function maps each element of X to a membership value between 0 and 1.

Fuzzy Logic Toolbox software includes 13 built-in membership function types. These functions are, in turn, built from several basic functions.

- Piecewise linear functions
- Gaussian distribution function
- Sigmoid curve
- Quadratic and cubic polynomial curves

The simplest membership functions are formed using straight lines. These straight-line membership functions have the advantage of simplicity.


- `trimf` – Triangular membership function
- `trapmf` – Trapezoidal membership function
- `linzmf` – Linear z-shaped membership function open to the left
- `linsmf` – Linear s-shaped membership function open to the right




Two membership functions are derived from *Gaussian* distributions: a simple Gaussian curve (`gaussmf`) and a two-sided composite of different Gaussian curves (`gauss2mf`).

The *generalized bell-shaped* membership function (`gbellmf`) has a similar smooth transition between 0 and 1. It has a third parameter that you can use to adjust the steepness of the transition from 0 to 1.

Because of their smoothness and concise notation, Gaussian and bell-shaped membership functions are popular methods for specifying fuzzy sets. Both of these curves have the advantage of being smooth and nonzero at all points.




Although the Gaussian and bell-shaped curves achieve smoothness, they are unable to specify asymmetric membership functions, which are important in certain applications. To do so, you can use the *sigmoidal* membership function (`sigmf`), which is a smooth membership function that is open to either the left or right. You can create asymmetric and closed membership functions based on either the difference (`dsigmf`) or product (`psigmf`) of two sigmoidal functions.



You can also create smooth membership functions using polynomial-based curves that are named for their shapes.

- `zmf` — Z-shaped membership function open to the left
- `smf` — S-shaped membership function open to the right
- `pimf` — Pi-shaped membership function, which is the product of an s-shaped and z-shaped membership function



You can also create your own custom membership functions. For more information, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

Logical Operations

Now that you understand the fuzzy inference, you need to see how fuzzy inference connects with logical operations.

The most important thing to realize about fuzzy logical reasoning is the fact that it is a superset of standard Boolean logic. In other words, if you keep the fuzzy values at their extremes of 1 (completely true), and 0 (completely false), standard logical operations hold. As an example, consider the following standard truth tables.

A	B	A and B
0	0	0
0	1	0
1	0	0
1	1	1

AND

A	B	A or B
0	0	0
0	1	1
1	0	1
1	1	1

OR

A	not A
0	1
1	0

NOT

Considering that, in fuzzy logic, the truth of any statement is a matter of degree, can these truth tables be altered? The input values can be real numbers between 0 and 1. What function preserves the results of the AND truth table (for example) and also extend to all real numbers between 0 and 1?

One answer is the *min* operation. That is, resolve the statement $A \text{ AND } B$, where A and B are limited to the range $(0,1)$, by using the function $\min(A,B)$. Using the same reasoning, you can replace the OR operation with the *max* function, so that $A \text{ OR } B$ becomes equivalent to $\max(A,B)$. Finally, the operation NOT A becomes equivalent to the operation $1 - A$. The previous truth table is completely unchanged by this substitution.

A	B	$\min(A,B)$
0	0	0
0	1	0
1	0	0
1	1	1

AND

A	B	$\max(A,B)$
0	0	0
0	1	1
1	0	1
1	1	1


OR

A	$1 - A$
0	1
1	0

NOT

Moreover, because there is a function behind the truth table rather than just the truth table itself, you can now consider values other than 1 and 0.

The next figure uses a graph to show the same information. In this figure, the truth table is converted to a plot of two fuzzy sets applied together to create one fuzzy set. The upper part of the figure displays plots corresponding to the preceding two-valued truth tables, while the lower part of the figure displays how the operations work over a continuously varying range of truth values A and B according to the fuzzy operations you have defined.



Given these three functions, you can resolve any construction using fuzzy sets and the fuzzy logical operation AND, OR, and NOT.

Additional Fuzzy Operators

In this case, you defined only one particular correspondence between two-valued and multivalued logical operations for AND, OR, and NOT. This correspondence is by no means unique.

In more general terms, you are defining what are known as the fuzzy intersection or conjunction (AND), fuzzy union or disjunction (OR), and fuzzy complement (NOT). The classical operators for these functions are: AND = *min*, OR = *max*, and NOT = additive complement. Typically, most fuzzy logic applications make use of these operations and leave it at that. In general, however, these functions are arbitrary. Fuzzy Logic Toolbox software uses the classical operator for the fuzzy complement as shown in the previous figure, but also enables you to customize the AND and OR operators.

The intersection of two fuzzy sets *A* and *B* is specified in general by a binary mapping *T*, which aggregates two membership functions as follows:

$$\mu_{A \cap B}(x) = T(\mu_A(x), \mu_B(x))$$

For example, the binary operator *T* may represent the multiplication of $\mu_A(x)$ and $\mu_B(x)$. These fuzzy intersection operators, which are usually referred to as *T*-norm (triangular norm) operators, meet the following basic requirements:

A *T*-norm operator is a binary mapping *T*(..) with the following properties:

- Boundary — $T(0, 0) = 0$, $T(a, 1) = T(1, a) = a$
- Monotonicity — $T(a, b) \leq T(c, d)$ if $a \leq c$ and $b \leq d$
- Commutativity — $T(a, b) = T(b, a)$
- Associativity — $T(a, T(b, c)) = T(T(a, b), c)$

The first requirement imposes the correct generalization to crisp sets. The second requirement implies that a decrease in the membership values in *A* or *B* cannot produce an increase in the

membership value in A intersection B . The third requirement indicates that the operator is indifferent to the order of the fuzzy sets to be combined. Finally, the fourth requirement allows us to take the intersection of any number of sets in any order of pair-wise groupings.

Like fuzzy intersection, the fuzzy union operator is specified in general by a binary mapping S :

$$\mu_{A \cup B}(x) = S(\mu_A(x), \mu_B(x))$$

For example, the binary operator S can represent the addition of $\mu_A(x)$ and $\mu_B(x)$. These fuzzy union operators, which are often referred to as T -conorm (or S -norm) operators, must satisfy the following basic requirements:

A T -conorm (or S -norm) operator is a binary mapping $S(.,.)$ with the following properties:

- Boundary — $S(1, 1) = 1$, $S(a, 0) = S(0, a) = a$
- Monotonicity — $S(a, b) \leq S(c, d)$ if $a \leq c$ and $b \leq d$
- Commutativity — $S(a, b) = S(b, a)$
- Associativity — $S(a, S(b, c)) = S(S(a, b), c)$

Several parameterized T -norms and dual T -conorms have been proposed in the past, such as those of Yager [11], Dubois and Prade [1], Schweizer and Sklar [8], and Sugeno [9]. Each of these provides a way to vary the gain on the function so that it can be very restrictive or very permissive.

If-Then Rules

Fuzzy sets and fuzzy operators are the subjects and verbs of fuzzy logic. These if-then rule statements are used to formulate the conditional statements that comprise fuzzy logic.

A single fuzzy if-then rule assumes the form

If x is A , then y is B

where A and B are linguistic values defined by fuzzy sets on the ranges (universes of discourse) X and Y , respectively. The if-part of the rule " x is A " is called the *antecedent* or premise, while the then-part of the rule " y is B " is called the *consequent* or conclusion. An example of such a rule might be
If service is good then tip is average

The concept *good* is represented as a number between 0 and 1, and so the antecedent is an interpretation that returns a single number between 0 and 1. Conversely, *average* is represented as a fuzzy set, and so the consequent is an assignment that assigns the entire fuzzy set B to the output variable y . In the if-then rule, the word *is* gets used in two entirely different ways depending on whether it appears in the antecedent or the consequent. In MATLAB terms, this usage is the distinction between a relational test using " $==$ " and a variable assignment using the " $=$ " symbol. A less confusing way of writing the rule would be

If service == good, then tip = average

In general, the input to an if-then rule is the current value for the input variable (in this case, *service*) and the output is an entire fuzzy set (in this case, *average*). This set will later be *defuzzified*, assigning one value to the output. The concept of defuzzification is described in the next section.

Interpreting an if-then rule involves two steps:

- Evaluation of the antecedent — *Fuzzifying* the inputs and applying any necessary *fuzzy operators*.
- Application of the result to the consequent.

The second step is known as *implication*. For an if-then rule, the antecedent, p , *implies* the consequent, q . In binary logic, if p is true, then q is also true ($p \rightarrow q$). In fuzzy logic, if p is true to some degree of membership, then q is also true to the same degree ($0.5p \rightarrow 0.5q$). In both cases, if p is false, then the value of q is undetermined.


The antecedent of a rule can have multiple parts.

If sky is gray and wind is strong and barometer is falling, then ...

In this case all parts of the antecedent are calculated simultaneously and resolved to a single number using the logical operators described in the preceding section. The consequent of a rule can also have multiple parts.

If temperature is cold, then hot water valve is open and cold water valve is shut

In this case, all consequents are affected equally by the result of the antecedent. How is the consequent affected by the antecedent? The consequent specifies a fuzzy set be assigned to the output. The *implication function* then modifies that fuzzy set to the degree specified by the antecedent. The most common ways to modify the output fuzzy set are truncation using the *min* function (where the fuzzy set is truncated as shown in the following figure) or scaling using the *prod* function (where the output fuzzy set is squashed). Both are supported by the toolbox, but you use truncation for the examples in this section.



Summary of If-Then Rules

Interpreting if-then rules is a three-part process. This process is explained in detail in the next section:

- 1 Fuzzify inputs:** Resolve all fuzzy statements in the antecedent to a degree of membership between 0 and 1. If there is only one part to the antecedent, then this is the degree of support for the rule.
- 2 Apply fuzzy operator to multiple part antecedents:** If there are multiple parts to the antecedent, apply fuzzy logic operators and resolve the antecedent to a single number between 0 and 1. This is the degree of support for the rule.
- 3 Apply implication method:** Use the degree of support for the entire rule to shape the output fuzzy set. The consequent of a fuzzy rule assigns an entire fuzzy set to the output. This fuzzy set is represented by a membership function that is chosen to indicate the qualities of the consequent. If the antecedent is only partially true, (i.e., is assigned a value less than 1), then the output fuzzy set is truncated according to the implication method.

In general, one rule alone is not effective. Two or more rules that can play off one another are needed. The output of each rule is a fuzzy set. The output fuzzy sets for each rule are then aggregated into a single output fuzzy set. Finally the resulting set is defuzzified, or resolved to a single number. “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14 shows how the whole process works from beginning to end for a particular type of fuzzy inference system called a *Mamdani type*.

References

- [1] Dubois, Didier, and Henri M. Prade. *Fuzzy Sets and Systems: Theory and Applications*. Mathematics in Science and Engineering, v. 144. New York: Academic Press, 1980.
- [2] Kaufmann, A., and Madan M. Gupta. *Introduction to Fuzzy Arithmetic: Theory and Applications*. Van Nostrand Reinhold Electrical/Computer Science and Engineering Series. New York, N.Y: Van Nostrand Reinhold Co, 1985.
- [3] Lee, C.C. ‘Fuzzy Logic in Control Systems: Fuzzy Logic Controller. I’. *IEEE Transactions on Systems, Man, and Cybernetics* 20, no. 2 (April 1990): 404-18. <https://doi.org/10.1109/21.52551>.
- [4] Lee, C.C. ‘Fuzzy Logic in Control Systems: Fuzzy Logic Controller. II’. *IEEE Transactions on Systems, Man, and Cybernetics* 20, no. 2 (April 1990): 419-35. <https://doi.org/10.1109/21.52552>.
- [5] Mamdani, E.H., and S. Assilian. ‘An Experiment in Linguistic Synthesis with a Fuzzy Logic Controller’. *International Journal of Man-Machine Studies* 7, no. 1 (January 1975): 1-13. [https://doi.org/10.1016/S0020-7373\(75\)80002-2](https://doi.org/10.1016/S0020-7373(75)80002-2).
- [6] Mamdani, E.H. ‘Advances in the Linguistic Synthesis of Fuzzy Controllers’. *International Journal of Man-Machine Studies* 8, no. 6 (November 1976): 669-78. [https://doi.org/10.1016/S0020-7373\(76\)80028-4](https://doi.org/10.1016/S0020-7373(76)80028-4).
- [7] Mamdani, E.H. ‘Application of Fuzzy Logic to Approximate Reasoning Using Linguistic Synthesis’. *IEEE Transactions on Computers* C-26, no. 12 (December 1977): 1182-91. <https://doi.org/10.1109/TC.1977.1674779>.

- [8] Schweizer, B. and A. Sklar, 'Associative functions and abstract semi-groups'. *Publ. Math. Debrecen* 10 (1963): 69-81.
- [9] Sugeno, M., "Fuzzy measures and fuzzy integrals: a survey," (M.M. Gupta, G. N. Saridis, and B.R. Gaines, editors) *Fuzzy Automata and Decision Processes*, pp. 89-102, North-Holland, NY, 1977.
- [10] Sugeno, Michio, ed. *Industrial Applications of Fuzzy Control*. Amsterdam ; New York : New York, N.Y., U.S.A: North-Holland ; Sole distributors for the U.S.A. and Canada, Elsevier Science Pub. Co, 1985.
- [11] Yager, Ronald R. 'On a General Class of Fuzzy Connectives'. *Fuzzy Sets and Systems* 4, no. 3 (November 1980): 235-42. [https://doi.org/10.1016/0165-0114\(80\)90013-5](https://doi.org/10.1016/0165-0114(80)90013-5).
- [12] Yager, Ronald R., and Dimitar P. Filev. 'Generation of Fuzzy Rules by Mountain Clustering'. *Journal of Intelligent and Fuzzy Systems* 2, no. 3 (1994): 209-19. <https://doi.org/10.3233/IFS-1994-2301>.
- [13] Zadeh, L.A. 'Fuzzy Sets'. *Information and Control* 8, no. 3 (June 1965): 338-53. [https://doi.org/10.1016/S0019-9958\(65\)90241-X](https://doi.org/10.1016/S0019-9958(65)90241-X).
- [14] Zadeh, Lotfi A. 'Outline of a New Approach to the Analysis of Complex Systems and Decision Processes'. *IEEE Transactions on Systems, Man, and Cybernetics* SMC-3, no. 1 (1973): 28-44. <https://doi.org/10.1109/TSMC.1973.5408575>.
- [15] Zadeh, L.A. 'The concept of a linguistic variable and its application to approximate reasoning. I'. *Information Sciences* 8, no. 3 (1975): 199-249. [https://doi.org/10.1016/0020-0255\(75\)90036-5](https://doi.org/10.1016/0020-0255(75)90036-5)
- [16] Zadeh, L.A. 'The concept of a linguistic variable and its application to approximate reasoning. II'. *Information Sciences* 8, no. 4 (1975): 301-357. [https://doi.org/10.1016/0020-0255\(75\)90046-8](https://doi.org/10.1016/0020-0255(75)90046-8)
- [17] Zadeh, L.A. 'The concept of a linguistic variable and its application to approximate reasoning. III'. *Information Sciences* 9, no. 1 (1975):43-80. [https://doi.org/10.1016/0020-0255\(75\)90017-1](https://doi.org/10.1016/0020-0255(75)90017-1)
- [18] Zadeh, L.A. 'Fuzzy Logic'. *Computer* 21, no. 4 (April 1988): 83-93. <https://doi.org/10.1109/2.53>.
- [19] Zadeh, L.A. 'Knowledge Representation in Fuzzy Logic'. *IEEE Transactions on Knowledge and Data Engineering* 1, no. 1 (March 1989): 89-100. <https://doi.org/10.1109/69.43406>.

See Also

More About


- "What Is Fuzzy Logic?" on page 1-3
- "Fuzzy Inference Process" on page 1-19
- "Fuzzy vs. Nonfuzzy Logic" on page 1-30

Fuzzy Inference Process

Fuzzy inference is the process of formulating the mapping from a given input to an output using fuzzy logic. The mapping then provides a basis from which decisions can be made, or patterns discerned. The process of fuzzy inference involves all the pieces that are described in “Membership Functions” on page 1-9, “Logical Operations” on page 1-13, and “If-Then Rules” on page 1-15.

This section describes the fuzzy inference process and uses the example of the two-input, one-output, three-rule tipping problem from “The Basic Tipping Problem” on page 2-16. The fuzzy inference system for this problem takes *service* and *food quality* as inputs and computes a tip percentage using the following rules.

- 1 If the service is poor or the food is rancid, then tip is cheap.
- 2 If the service is good, then tip is average.
- 3 If the service is excellent or the food is delicious, then tip is generous.



The parallel nature of the rules is an important aspect of fuzzy logic systems. Instead of sharp switching between modes based on breakpoints, logic flows smoothly from regions where one rule or another dominates.

The fuzzy inference process has the following steps.


- Fuzzification of the input variables on page 1-20
- Application of the fuzzy operator (AND or OR) in the antecedent on page 1-20
- Implication from the antecedent to the consequent on page 1-21
- Aggregation of the consequents across the rules on page 1-22
- Defuzzification on page 1-22

A fuzzy inference diagram on page 1-23 displays all parts of the fuzzy inference process — from fuzzification through defuzzification.

Fuzzify Inputs

The first step is to take the inputs and determine the degree to which they belong to each of the appropriate fuzzy sets via membership functions (fuzzification). In Fuzzy Logic Toolbox software, the input is always a crisp numerical value limited to the universe of discourse of the input variable (in this case, the interval from 0 through 10). The output is a fuzzy degree of membership in the qualifying linguistic set (always the interval from 0 through 1). Fuzzification of the input amounts to either a table lookup or a function evaluation.

This example is built on three rules, and each of the rules depends on resolving the inputs into several different fuzzy linguistic sets: service is poor, service is good, food is rancid, food is delicious, and so on. Before the rules can be evaluated, the inputs must be fuzzified according to each of these linguistic sets. For example, to what extent is the food delicious? The following figure shows how well the food at the hypothetical restaurant (rated on a scale from 0 through 10) qualifies as the linguistic variable delicious using a membership function. In this case, we rate the food as an 8, which, given the graphical definition of delicious, corresponds to $\mu = 0.7$ for the delicious membership function.



In this manner, each input is fuzzified over all the qualifying membership functions required by the rules.

Apply Fuzzy Operator

After the inputs are fuzzified, you know the degree to which each part of the antecedent is satisfied for each rule. If the antecedent of a rule has more than one part, the fuzzy operator is applied to obtain one number that represents the result of the rule antecedent. This number is then applied to the output function. The input to the fuzzy operator is two or more membership values from fuzzified input variables. The output is a single truth value.


As described in “Logical Operations” on page 1-13, any number of well-defined methods can fill in for the AND operation or the OR operation. In the toolbox, two built-in AND methods are supported: *min* (minimum) and *prod* (product). Two built-in OR methods are also supported: *max* (maximum) and *probor* (probabilistic OR). The probabilistic OR method (also known as the algebraic sum) is calculated according to the equation:

$$\text{probor}(a,b) = a + b - ab$$

In addition to these built-in methods, you can create your own methods for AND and OR by writing any function and setting that to be your method of choice. For more information, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

The following figure demonstrates the OR operator *max* by evaluating the antecedent of the third rule of the tipping calculation. For the given service and food ratings, the two elements of the antecedent


(service is excellent and food is delicious) produce the fuzzy membership values 0.0 and 0.7, respectively. The fuzzy OR operator selects the maximum of the two values, 0.7. The probabilistic OR method would still result in 0.7.



Apply Implication Method

Before applying the implication method, you must determine the rule weight. Every rule has a *weight* (a number from 0 through 1), which is applied to the number given by the antecedent. Generally, this weight is 1 (as it is for this example) and thus has no effect on the implication process. However, you can decrease the effect of one rule relative to the others by changing its weight value to something other than 1.

After proper weighting has been assigned to each rule, the implication method is implemented. A consequent is a fuzzy set represented by a membership function, which weights appropriately the linguistic characteristics that are attributed to it. The consequent is reshaped using a function associated with the antecedent (a single number). The input for the implication process is a single number given by the antecedent, and the output is a fuzzy set. Implication is implemented for each rule. Two built-in methods are supported, and they are the same functions that are used by the AND method: *min* (minimum), which truncates the output fuzzy set, and *prod* (product), which scales the output fuzzy set.



Note Sugeno systems always use the product implication method.


Aggregate All Outputs

Since decisions are based on testing all the rules in a FIS, the rule outputs must be combined in some manner. Aggregation is the process by which the fuzzy sets that represent the outputs of each rule are combined into a single fuzzy set. Aggregation only occurs once for each output variable, which is before the final defuzzification step. The input of the aggregation process is the list of truncated output functions returned by the implication process for each rule. The output of the aggregation process is one fuzzy set for each output variable.

As long as the aggregation method is commutative, then the order in which the rules are executed is unimportant. Three built-in methods are supported.

- max (maximum)
- probor (probabilistic OR)
- sum (sum of the rule output sets)

In the following diagram, all three rules are displayed to show how the rule outputs are aggregated into a single fuzzy set whose membership function assigns a weighting for every output (tip) value.




Note Sugeno systems always use the sum aggregation method.

Defuzzify

The input for the defuzzification process is the aggregate output fuzzy set and the output is a single number. As much as fuzziness helps the rule evaluation during the intermediate steps, the final

desired output for each variable is generally a single number. However, the aggregate of a fuzzy set encompasses a range of output values, and so must be defuzzified to obtain a single output value from the set.


There are five built-in defuzzification methods supported: centroid, bisector, middle of maximum (the average of the maximum value of the output set), largest of maximum, and smallest of maximum. Perhaps the most popular defuzzification method is the centroid calculation, which returns the center of the area under the aggregate fuzzy set, as shown in the following figure.



While the aggregate output fuzzy set covers a range from 0% though 30%, the defuzzified value is between 5% and 25%. These limits correspond to the centroids of the cheap and generous membership functions, respectively.


Fuzzy Inference Diagram

The fuzzy inference diagram is the composite of all the smaller diagrams presented so far in this section. It simultaneously displays all parts of the fuzzy inference process you have examined. Information flows through the fuzzy inference diagram as shown in the following figure.



In this figure, the flow proceeds up from the inputs in the lower left, across each row, and then down the rule outputs to the lower right. This compact flow shows everything at once, from linguistic variable fuzzification all the way through defuzzification of the aggregate output.

The following figure shows the actual full-size fuzzy inference diagram for the basic tipping problem. Using a fuzzy inference diagram, you can learn a lot about how the system operates. For instance, for the particular inputs in this diagram, you can see that the implication method is truncation with the *min* function. The *max* function is used for the fuzzy OR operation. Rule 3 (the bottom-most row in the diagram shown previously) has the strongest influence on the output. The Rule Viewer described in “The Rule Viewer” on page 2-27 is an implementation of the fuzzy inference diagram.



See Also

More About

- “Foundations of Fuzzy Logic” on page 1-7

Defuzzification Methods


This example describes the built-in methods for defuzzifying the output fuzzy set of a type-1 Mamdani fuzzy inference system.

Consider the following output fuzzy set, which is an aggregation of three scaled trapezoidal membership functions.

```
x = 0:0.1:20;

mf1 = trapmf(x,[0 2 8 12]);
mf2 = trapmf(x,[5 7 12 14]);
mf3 = trapmf(x,[12 13 18 19]);
mf = max(0.5*mf2,max(0.9*mf1,0.1*mf3));

figure('Tag','defuzz')
plot(x,mf,'LineWidth',3)
h_gca = gca;
h_gca.YTick = [0 .5 1] ;
ylim([-1 1])
```



Fuzzy Logic Toolbox™ software supports five built-in methods for computing a single crisp output value for such a fuzzy set.

- Centroid
- Bisector

- Middle of maximum
- Smallest of maximum
- Largest of maximum

You can also define your own custom defuzzification method. For more information, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

Centroid

Centroid defuzzification returns the center of gravity of the fuzzy set along the x-axis. If you think of the area as a plate with uniform thickness and density, the centroid is the point along the x-axis about which the fuzzy set would balance. The centroid is computed using the following formula, where $\mu(x_i)$ is the membership value for point x_i in the universe of discourse.


$$x_{\text{Centroid}} = \frac{\sum_i \mu(x_i) x_i}{\sum_i \mu(x_i)}$$

Compute the centroid of the fuzzy set.

```
xCentroid = defuzz(x,mf, 'centroid');
```

Indicate the centroid defuzzification result on the original plot.

```
hCentroid = line([xCentroid xCentroid],[-0.2 1.2], 'Color','k');  
tCentroid = text(xCentroid,-0.2, 'centroid', 'FontWeight','bold');
```




Bisector

The bisector method finds the vertical line that divides the fuzzy set into two sub-regions of equal area. It is sometimes, but not always, coincident with the centroid line.

```
xBisector = defuzz(x,mf,'bisector');
```

Indicate the bisector result on the original plot, and gray out the centroid result.

```
hBisector = line([xBisector xBisector],[-0.4 1.2],'Color','k');
tBisector = text(xBisector,-0.4,'bisector','FontWeight','bold');
gray = 0.7*[1 1 1];
hCentroid.Color = gray;
tCentroid.Color = gray;
```



Middle, Smallest, and Largest of Maximum

MOM, SOM, and LOM stand for middle, smallest, and largest of maximum, respectively. In this example, since the aggregate fuzzy set has a plateau at its maximum value, the MOM, SOM, and LOM defuzzification results have distinct values. If the aggregate fuzzy set has a unique maximum, then MOM, SOM, and LOM all produce the same value.


```
xMOM = defuzz(x,mf,'mom');
xSOM = defuzz(x,mf,'som');
xLOM = defuzz(x,mf,'lom');
```

Indicate the MOM, SOM, and LOM results on the original plot, and gray out the bisector result.

```

hMOM = line([xMOM xMOM],[-0.7 1.2],'Color','k');
tMOM = text(xMOM,-0.7,'MOM','FontWeight','bold');
hSOM = line([xSOM xSOM],[-0.7 1.2],'Color','k');
tSOM = text(xSOM,-0.7,'SOM','FontWeight','bold');
hLOM = line([xLOM xLOM],[-0.7 1.2],'Color','k');
tLOM = text(xLOM,-0.7,'LOM','FontWeight','bold');
hBisector.Color = gray;
tBisector.Color = gray;

```



Choosing Defuzzification Method


In general, using the default centroid method is good enough for most applications. Once you have created your initial fuzzy inference system, you can try other defuzzification methods to see if any improve your inference results.

Highlight the centroid result, and gray out the MOM, SOM, and LOM results.

```

hCentroid.Color = 'red';
tCentroid.Color = 'red';
hMOM.Color = gray;
tMOM.Color = gray;
hSOM.Color = gray;
tSOM.Color = gray;
hLOM.Color = gray;
tLOM.Color = gray;

```



See Also

More About

- “Foundations of Fuzzy Logic” on page 1-7
- “Fuzzy Inference Process” on page 1-19

Fuzzy vs. Nonfuzzy Logic

Basic Tipping Problem

To illustrate the value of fuzzy logic, examine both linear and fuzzy approaches to the following problem:

What is the right amount to tip your waitperson?

First, work through this problem the conventional (nonfuzzy) way, writing MATLAB® commands that spell out linear and piecewise-linear relations. Then, look at the same system using fuzzy logic.


Basic Tipping Problem. Given a number from 0 through 10 that represents the quality of service at a restaurant (where 10 is excellent), what should the tip be?

This problem is based on tipping as it is typically practiced in the United States. An average tip for a meal in the US is 15%, though the actual amount can vary depending on the quality of the service provided.

Nonfuzzy Approach


Begin with the simplest possible relationship. Suppose that the tip always equals 15% of the total bill.

```
service = 0:.5:10;  
tip = 0.15*ones(size(service));  
plot(service,tip)  
xlabel('Service')  
ylabel('Tip')  
ylim([0.05 0.25])
```

This relationship does not account for the quality of the service, so you must add a term to the equation. Since service is rated on a scale from 0 through 10, you the tip increase linearly from 5% if the service is bad to 25% if the service is excellent. Now the relation looks like the following plot:

```
tip = (.20/10)*service+0.05;  
plot(service,tip)  
xlabel('Service')  
ylabel('Tip')  
ylim([0.05 0.25])
```




The formula does what you want it to do, and is straight forward. However, you may want the tip to reflect the quality of the food as well. This extension of the problem is defined as follows.

Extended Tipping Problem. Given two sets of numbers from 0 through 10 (where 10 is excellent) that respectively represent the quality of the service and the quality of the food at a restaurant, what should the tip be?


See how the formula is affected now that you have added another variable.

```
food = 0:.5:10;  
[F,S] = meshgrid(food,service);  
tip = (0.20/20).*(S+F)+0.05;  
surf(S,F,tip)  
xlabel('Service')  
ylabel('Food')  
zlabel('Tip')
```




In this case, the results look satisfactory, but when you look at them closely, they do not seem right. Suppose that you want the service to be a more important factor than the food quality. Specify that service accounts for 80% of the overall tipping grade and the food makes up the other 20%.

```
servRatio = 0.8;
tip = servRatio*(0.20/10*S+0.05) + ...
      (1-servRatio)*(0.20/10*F+0.05);
surf(S,F,tip)
xlabel('Service')
ylabel('Food')
zlabel('Tip')
```



The response is still somehow too uniformly linear. Suppose that you want more of a flat response in the middle, that is, you want to give a 15% tip in general, but want to also specify a variation if the service is exceptionally good or bad. This factor, in turn, means that the previous linear mappings no longer apply. You can still use the linear calculation with a piecewise linear construction. Now, return to the one-dimensional problem of just considering the service. You can create a simple conditional tip assignment using logical indexing.

```
tip = zeros(size(service));
tip(service<3) = (0.10/3)*service(service<3)+0.05;
tip(service>=3 & service<7) = 0.15;
tip(service>=7 & service<=10) = ...
    (0.10/3)*(service(service>=7 & service<=10)-7)+0.15;
plot(service,tip)
xlabel('Service')
ylabel('Tip')
ylim([0.05 0.25])
```




Suppose that you extend this approach to two dimensions, where you account for food quality again.

```

servRatio = 0.8;
tip = zeros(size(S));
tip(S<3) = ((0.10/3)*S(S<3)+0.05)*servRatio + ...
    (1-servRatio)*(0.20/10*F(S<3)+0.05);
tip(S>=3 & S<7) = (0.15)*servRatio + ...
    (1-servRatio)*(0.20/10*F(S>=3 & S<7)+0.05);
tip(S>=7 & S<=10) = ((0.10/3)*(S(S>=7 & S<=10)-7)+0.15)*servRatio + ...
    (1-servRatio)*(0.20/10*F(S>=7 & S<=10)+0.05);
surf(S,F,tip)
xlabel('Service')
ylabel('Food')
zlabel('Tip')

```



The plot looks good, but the function is surprisingly complicated. It is even not apparent how the algorithm works to someone who did not see the original design process.

Fuzzy Logic Approach

In general, you want to capture the essentials of this problem, leaving aside all the factors that could be arbitrary. If you make a list of what really matters in this problem, you could end up with the following rule descriptions.

Tipping Problem Rules - Service Factor

- If service is poor, then tip is cheap
- If service is good, then tip is average
- If service is excellent, then tip is generous

The order in which the rules are presented here is arbitrary. It does not matter which rules come first. To include the effect of food quality on the tip, add the following two rules.

Tipping Problem Rules - Food Factor

- If food is rancid, then tip is cheap
- If food is delicious, then tip is generous

You can combine the two different lists of rules into one list of three rules like so.

Tipping Problem Rules - Both Service and Food Factors

- If service is poor or the food is rancid, then tip is cheap
- If service is good, then tip is average
- If service is excellent or food is delicious, then tip is generous


These three rules are the core of your solution and they correspond to the rules for a fuzzy logic system. When you give mathematical meaning to the linguistic variables (what is an average tip, for example) you have a complete fuzzy inference system. The methodology of fuzzy logic must also consider:

- How are the rules all combined?
- How do I define mathematically what an average tip is?

Problem Solution

The following plot represents the fuzzy logic system that solves the tipping problem.

```
gensurf(readfis('tipper'))
```



This plot was generated by the three rules that accounted for both service and food factors.

Observations Consider some observations about the example so far. You found a piecewise linear relation that solved the problem. It worked, but it was problematic to derive, and when you wrote it down as code, it was not easy to interpret. Conversely, the fuzzy logic system is based on some common sense statements. Also, you were able to add two more rules to the list that influenced the shape of the overall output without needing to undo what had already been done.

Moreover, by using fuzzy logic rules, the maintenance of the structure of the algorithm decouples along fairly clean lines. The notion of an average tip can change from day to day, city to city, country to country. However, the underlying logic is the same: if the service is good, the tip should be average.

Recalibrating the Method You can recalibrate the method quickly by simply shifting the fuzzy set that defines average without rewriting the fuzzy logic rules.

You can shift lists of piecewise linear functions, but there is a greater likelihood for difficult recalibration.

In the following example, the piecewise linear tipping problem is rewritten to make it more generic. It performs the same function as before, only now the constants can be easily changed.

```
lowTip = 0.05;
averTip = 0.15;
highTip = 0.25;
tipRange = highTip-lowTip;
badService = 0;
okayService = 3;
goodService = 7;
greatService = 10;
serviceRange = greatService-badService;
badFood = 0;
greatFood = 10;
foodRange = greatFood-badFood;

% If service is poor or food is rancid, tip is cheap
if service<okayService
    tip = (((averTip-lowTip)/(okayService-badService)) ...
        *service+lowTip)*servRatio + ...
        (1-servRatio)*(tipRange/foodRange*food+lowTip);

% If service is good, tip is average
elseif service<goodService
    tip = averTip*servRatio + (1-servRatio)* ...
        (tipRange/foodRange*food+lowTip);

% If service is excellent or food is delicious, tip is generous
else
    tip = (((highTip-averTip)/ ...
        (greatService-goodService))* ...
        (service-goodService)+averTip)*servRatio + ...
        (1-servRatio)*(tipRange/foodRange*food+lowTip);
end
```

As with all code, the more generality that is introduced, the less precise the algorithm becomes. You can improve clarity by adding more comments, or perhaps rewriting the algorithm in slightly more self-evident ways. But, the piecewise linear methodology is not the optimal way to resolve this issue.

If you remove everything from the algorithm except for three comments, what remain are exactly the fuzzy logic rules you previously wrote down.

- If service is poor or food is rancid, tip is cheap
- If service is good, tip is average

- If service is excellent or food is delicious, tip is generous

Fuzzy logic uses language that is clear to you and that also has meaning to the computer, which is why it is a successful technique for bridging the gap between people and machines.

By making the equations as simple as possible (linear) you make things simpler for the machine, but more complicated for you. However, the limitation is no longer the computer - it is your mental model of what the computer is doing. Fuzzy logic lets the machine work with your preferences rather than the other way around.

See Also

Related Examples

- “Build Fuzzy Systems at the Command Line” on page 2-31
- “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14

Fuzzy Inference System Modeling

- “Mamdani and Sugeno Fuzzy Inference Systems” on page 2-2
- “Type-2 Fuzzy Inference Systems” on page 2-7
- “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14
- “Build Fuzzy Systems at the Command Line” on page 2-31
- “Build Fuzzy Systems Using Custom Functions” on page 2-40
- “Fuzzy Trees” on page 2-52
- “Fuzzy PID Control with Type-2 FIS” on page 2-58
- “Fuzzy Logic Image Processing” on page 2-72

Mamdani and Sugeno Fuzzy Inference Systems

Fuzzy Logic Toolbox software supports two types of fuzzy inference systems:

- Mamdani systems
- Sugeno systems


Fuzzy Inference System	Advantages
Mamdani	<ul style="list-style-type: none"> • Intuitive • Well-suited to human input • More interpretable rule base • Have widespread acceptance
Sugeno	<ul style="list-style-type: none"> • Computationally efficient • Work well with linear techniques, such as PID control • Work well with optimization and adaptive techniques • Guarantee output surface continuity • Well-suited to mathematical analysis

Mamdani Fuzzy Inference Systems

Mamdani fuzzy inference was first introduced as a method to create a control system by synthesizing a set of linguistic control rules obtained from experienced human operators [1]. In a Mamdani system, the output of each rule is a fuzzy set.

Since Mamdani systems have more intuitive and easier to understand rule bases, they are well-suited to expert system applications where the rules are created from human expert knowledge, such as medical diagnostics.

The inference process of a Mamdani system is described in “Fuzzy Inference Process” on page 1-19 and summarized in the following figure.




The output of each rule is a fuzzy set derived from the output membership function and the implication method of the FIS. These output fuzzy sets are combined into a single fuzzy set using the aggregation method of the FIS. Then, to compute a final crisp output value, the combined output fuzzy set is defuzzified using one of the methods described in “Defuzzification Methods” on page 1-25.

Sugeno Fuzzy Inference Systems

Sugeno fuzzy inference, also referred to as Takagi-Sugeno-Kang fuzzy inference, uses *singleton* output membership functions that are either constant or a linear function of the input values. The defuzzification process for a Sugeno system is more computationally efficient compared to that of a Mamdani system, since it uses a weighted average or weighted sum of a few data points rather than compute a centroid of a two-dimensional area. [2]

You can convert a Mamdani system into a Sugeno system using the `convertToSugeno` function. The resulting Sugeno system has constant output membership functions that correspond to the centroids of the Mamdani output membership functions.

Each rule in a Sugeno system operates as shown in the following diagram, which shows a two-input system with input values x and y .



Each rule generates two values:

- z_i — Rule output level, which is either a constant value or a linear function of the input values:

$$z_i = a_i x + b_i y + c_i$$

Here, x and y are the values of input 1 and input 2, respectively, and a_i , b_i , and c_i are constant coefficients. For a zero-order Sugeno system, z_i is a constant ($a = b = 0$).

- w_i — Rule firing strength derived from the rule antecedent

$$w_i = \text{AndMethod}(F_1(x), F_2(y))$$

Here, $F_1(\dots)$ and $F_2(\dots)$ are the membership functions for inputs 1 and 2, respectively.

The output of each rule is the weighted output level, which is the product of w_i and z_i .


The easiest way to visualize first-order Sugeno systems (a and b are nonzero) is to think of each rule as defining the location of a moving singleton. That is, the singleton output spikes can move around in a linear fashion within the output space, depending on the input values. The rule firing strength then defines the size of the singleton spike.

The final output of the system is the weighted average over all rule outputs:

$$\text{Final Output} = \frac{\sum_{i=1}^N w_i z_i}{\sum_{i=1}^N w_i}$$

where N is the number of rules.

The following figure shows the fuzzy inference process for a Sugeno system.



Note Sugeno systems always use product implication and sum aggregation.

Because of the linear dependence of each rule on the input variables, the Sugeno method is ideal for acting as an interpolating supervisor of multiple linear controllers that are to be applied, respectively, to different operating conditions of a dynamic nonlinear system. For example, the performance of an aircraft may change dramatically with altitude and Mach number. Linear controllers, though easy to compute and suited to any given flight condition, must be updated regularly and smoothly to keep up with the changing state of the flight vehicle. A Sugeno fuzzy inference system is suited to the task of smoothly interpolating the linear gains that would be applied across the input space; it is a natural and efficient gain scheduler. Similarly, a Sugeno system is suited for modeling nonlinear systems by interpolating between multiple linear models.

References

- [1] Mamdani, E.H., and S. Assilian. 'An Experiment in Linguistic Synthesis with a Fuzzy Logic Controller'. *International Journal of Man-Machine Studies* 7, no. 1 (January 1975): 1-13. [https://doi.org/10.1016/S0020-7373\(75\)80002-2](https://doi.org/10.1016/S0020-7373(75)80002-2).
- [2] Sugeno, Michio, ed. *Industrial Applications of Fuzzy Control*. Amsterdam ; New York : New York, N.Y., U.S.A: North-Holland ; Sole distributors for the U.S.A. and Canada, Elsevier Science Pub. Co, 1985.

See Also

More About

- “Foundations of Fuzzy Logic” on page 1-7
- “Fuzzy Inference Process” on page 1-19
- “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14
- “Build Fuzzy Systems at the Command Line” on page 2-31
- “Build Fuzzy Systems Using Custom Functions” on page 2-40


Type-2 Fuzzy Inference Systems

For any value in the universe of discourse, a traditional type-1 membership function has a single membership value. Therefore, while a type-1 membership function models the degree of membership in a given linguistic set, it does not model uncertainty in the degree of membership. To model such uncertainty, you can use interval type-2 membership functions. In such type-2 membership functions, the degree of membership can have a range of values.

For examples that use type-2 fuzzy inference systems, see “Fuzzy PID Control with Type-2 FIS” on page 2-58 and “Predict Chaotic Time Series Using Type-2 FIS” on page 3-58.

Interval Type-2 Membership Functions

An interval type-2 membership function is defined by an upper and lower membership function. The upper membership function (UMF) is equivalent to a traditional type-1 membership function. The lower membership function (LMF) is less than or equal to the upper membership function for all possible input values. The region between the UMF and LMF is the footprint of uncertainty (FOU). The following diagram shows the UMF (red), the LMF (blue), and the FOU (shaded) for a type-2 triangular membership function.



For each input value in the universe of discourse, the degree of membership is the range of values between the LMF and UMF values.

Type-2 Fuzzy Inference Systems

Using Fuzzy Logic Toolbox software, you can create both type-2 Mamdani and Sugeno fuzzy inference systems.

- In type-2 Mamdani systems, both the input and output membership functions are type-2 fuzzy sets.
- In type-2 Sugeno systems, only the input membership functions are type-2 fuzzy sets. The output membership functions are the same as for a type-1 Sugeno system — constant or a linear function of the input values.

To create type-2 Mamdani and Sugeno systems, use `mamfistype2` and `sugfistype2` objects, respectively. These objects have the same parameters as the type-1 `mamfis` and `sugfis` objects along with an additional `TypeReductionMethod` parameter.

You can also create a type-2 fuzzy inference system by converting an existing type-1 system, such as one created using the `genfis` function. To do so, use the `convertToType2` function.


Once you create a type-2 fuzzy inference system, you can:

- Evaluate the fuzzy system using the `evalfis` functions
- Simulate the fuzzy system using the Fuzzy Logic Controller block
- Tune the parameters of the fuzzy system using the `tunefis` function
- Deploy the fuzzy system as described in “Deploy Fuzzy Inference Systems” on page 6-2


Fuzzy Inference Process for Type-2 Fuzzy Systems

Antecedent Processing

For type-2 fuzzy inference systems, input values are fuzzified by finding the corresponding degree of membership in both the UMFs and LMFs from the rule antecedent. Doing so generates two fuzzy values for each type-2 membership function. For example, the fuzzification in the following figure shows the membership value in the upper membership function (f_U) and the lower membership function (f_L).




Next, a range of rule firing strengths is found by applying the fuzzy operator to the fuzzified values of the type-2 membership functions, as shown in the following figure. The maximum value of this range (w_U) is the result of applying the fuzzy operator to the fuzzy values from the UMFs. The minimum value (w_L) is the result of applying the fuzzy operator to the fuzzy values from the LMFs



Antecedent processing is the same for both Mamdani and Sugeno systems.

Consequent Processing

For a Mamdani system, the implication method clips (min implication) or scales (prod implication) the UMF and LMF of the output type-2 membership function using the rule firing range limits. This process produces an output fuzzy set for each rule. The following figure shows the output fuzzy set (dark gray region) produced by applying min implication to the UMF (red) and LMF (blue).



For a type-2 Sugeno system, the output level z_i for the i th rule is computed in the same manner as for a type-1 Sugeno system.

$$z_i = c_0^i + \sum_{j=1}^M c_j^i x_j$$


Here, j is the input index, x_j is the value of the j th input variable, and the c terms are the upper membership function parameters

Unlike a type-1 Sugeno system, the rule firing strengths are not used to process the consequent of each rule. Instead, the output level and rule firing strengths are used during the aggregation process.

Aggregation

The goal of the aggregation stage is to derive a single type-2 fuzzy set from the rule output fuzzy sets.

For a type-2 Mamdani system, the software finds an aggregate type-2 fuzzy set by applying the aggregation method to the UMFs and LMFs of the output fuzzy sets of all the rules. The following figure shows the aggregation of two type-2 fuzzy sets (the outputs for a two-rule system) using max aggregation.




For a type-2 Sugeno system, the aggregate fuzzy set is derived using the following steps:

- 1 Sort the rule output levels (z_i) from all the rules into ascending order. These output level values define the universe of discourse for the aggregate type-2 fuzzy set.
- 2 For each output level, define the UMF value using the maximum firing range value from the corresponding rule.
- 3 For each output level, define the LMF value using the minimum firing range value from the corresponding rule.

For example, suppose you have a type-2 Sugeno system with seven rules. Further, assume these rules have the following output levels and firing range limits.

Rule	Output Level (z)	Minimum Firing Value	Maximum Firing Value
1	6.3	0.1	0.5
2	4.9	0.4	0.5
3	1.6	0.3	0.5
4	5.8	0.5	0.7
5	5.4	0.2	0.6
6	0.7	0.5	0.8
7	3.2	0.2	0.7


The following figure shows the aggregated type-2 fuzzy set for this Sugeno system with its associated UMF (red) and LMF (blue).



Type Reduction and Defuzzification

To find the final crisp output value for the inference process, the aggregate type-2 fuzzy set is first reduced to an interval type-1 fuzzy set, which is a range with lower limit c_L and upper limit c_R . This interval type-1 fuzzy set is commonly referred to as the centroid of the type-2 fuzzy set. In theory, this centroid is the average of the centroids of all the type-1 fuzzy sets embedded in the type-2 fuzzy set. In practice, it is not possible to compute the exact values of c_L and c_R . Instead, iterative type-reduction methods are used to estimate these values.

For a given aggregate type-2 fuzzy set, the approximate values of c_L and c_R are the centroids of the following type-1 fuzzy sets (green).



Mathematically, these centroids are found using the following equations. [1]

$$c_L \approx \frac{\sum_{i=1}^L x_i \mu_{umf}(x_i) + \sum_{i=L+1}^N x_i \mu_{lmf}(x_i)}{\sum_{i=1}^L \mu_{umf}(x_i) + \sum_{i=L+1}^N \mu_{lmf}(x_i)}$$

$$c_R \approx \frac{\sum_{i=1}^R x_i \mu_{lmf}(x_i) + \sum_{i=R+1}^N x_i \mu_{umf}(x_i)}{\sum_{i=1}^R \mu_{lmf}(x_i) + \sum_{i=R+1}^N \mu_{umf}(x_i)}$$

Here:

- N is the number of samples taken across the output variable range, specified using `evalfisOptions`.
- x_i is the i th output value sample.
- μ_{umf} is the upper membership function.
- μ_{lmf} is the lower membership function.
- L and R are switch points that are estimated by the various type-reduction methods. For a list of supported methods, see “Type-Reduction Methods” on page 2-12.

For both Mamdani and Sugeno systems, the final defuzzified output value (y) is the average of the two centroid values from the type reduction process.

$$y = \frac{c_L + c_R}{2}$$

Type-Reduction Methods

Fuzzy Logic Toolbox software supports four built-in type-reduction methods. These algorithms differ in their initialization methods, assumptions, computational efficiency, and terminating conditions.

To set the type-reduction method for a type-2 fuzzy system, set the `TypeReduction` property of the `mamfistype2` or `sugfistype2` object.

Method	TypeReduction property Value	Description
Karnik-Mendel (KM) [2]	"karnikmendel"	First type-reduction method developed
Enhanced Karnik-Mendel (EKM) [3]	"ekm"	Modification of the Karnik-Mendel algorithm with an improved initialization, modified termination condition, and improved computational efficiency
Iterative algorithm with stop condition (IASC) [4]	"iasc"	Iterative improvement to brute force methods
Enhanced iterative algorithm with stop condition (EIASC) [5]	"eiasc"	Improved version of the IASC algorithm

In general, the computational efficiency of these methods improve as you move down the table.

You can also use your own custom type-reduction method. For more information, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

References

- [1] Mendel, Jerry M., Hani Hagrass, Woei-Wan Tan, William W. Melek, and Hao Ying. *Introduction to Type-2 Fuzzy Logic Control: Theory and Applications*. Hoboken, New Jersey: IEEE Press, John Wiley & Sons, 2014.
- [2] Karnik, Nilesh N., and Jerry M. Mendel. ‘Centroid of a Type-2 Fuzzy Set’. *Information Sciences* 132, no. 1-4 (February 2001): 195-220. [https://doi.org/10.1016/S0020-0255\(01\)00069-X](https://doi.org/10.1016/S0020-0255(01)00069-X).

- [3] Wu, D. and J.M. Mendel, "Enhanced Karnik-Mendel algorithms," *IEEE Transactions on Fuzzy Systems*, vol. 17, pp. 923-934. (2009)
- [4] Duran, K., H. Bernal, and M. Melgarejo, "Improved iterative algorithm for computing the generalized centroid of an interval type-2 fuzzy set," *Annual Meeting of the North American Fuzzy Information Processing Society*, pp. 190-194. (2008)
- [5] Wu, D. and M. Nie, "Comparison and practical implementations of type-reduction algorithms for type-2 fuzzy sets and systems," *Proceedings of FUZZ-IEEE*, pp. 2131-2138 (2011)

See Also

mamfistype2 | sugfistype2

More About

- "Mamdani and Sugeno Fuzzy Inference Systems" on page 2-2
- "Fuzzy PID Control with Type-2 FIS" on page 2-58
- "Predict Chaotic Time Series Using Type-2 FIS" on page 3-58

Build Fuzzy Systems Using Fuzzy Logic Designer

Fuzzy Logic Toolbox Graphical User Interface Tools

This example shows how to build a fuzzy inference system (FIS) for the tipping example, described in “The Basic Tipping Problem” on page 2-16, using the Fuzzy Logic Toolbox UI tools. These tools support only type-1 fuzzy systems.


You use the following tools to build, edit, and view fuzzy inference systems:

- **Fuzzy Logic Designer** to handle the high-level issues for the system — How many input and output variables? What are their names?


Fuzzy Logic Toolbox software does not limit the number of inputs. However, the number of inputs may be limited by the available memory of your machine. If the number of inputs is too large, or the number of membership functions is too big, then it may also be difficult to analyze the FIS using the other tools.

- **Membership Function Editor** on page 2-20 to define the shapes of all the membership functions associated with each variable
- **Rule Editor** on page 2-25 to edit the list of rules that defines the behavior of the system.
- **Rule Viewer** on page 2-27 to view the fuzzy inference diagram. Use this viewer as a diagnostic to see, for example, which rules are active, or how individual membership function shapes influence the results
- **Surface Viewer** on page 2-29 to view the dependency of one of the outputs on any one or two of the inputs; that is, it generates and plots an output surface map for the system.

These UIs are dynamically linked, in that changes you make to the FIS using one of them, affect what you see on any of the other open UIs. For example, if you change the names of the membership functions in the Membership Function Editor, the changes are reflected in the rules shown in the Rule Editor. You can use the UIs to read and write variables both to the MATLAB workspace and to a file (the read-only viewers can still exchange plots with the workspace and save them to a file). You can have any or all of them open for any given system or have multiple editors open for any number of fuzzy systems.



The following figure shows how the main components of a FIS and the three editors fit together. The two viewers examine the behavior of the entire system.



In addition to these five primary UIs, the toolbox includes the graphical **Neuro-Fuzzy Designer**, which you use to build and analyze Sugeno-type adaptive neuro-fuzzy inference systems.

The Fuzzy Logic Toolbox UIs do not support building a FIS using data. If you want to use data to build a FIS, use one of the following techniques:

- `genfis` to generate a Sugeno-type FIS. Then, select **File > Import** in **Fuzzy Logic Designer** to import the FIS and perform fuzzy inference, as described in “Fuzzy Logic Designer” on page 2-16.
- Neuro-adaptive learning techniques to model the FIS, as described in “Neuro-Adaptive Learning and ANFIS” on page 3-171.

If you want to use MATLAB workspace variables, use the command-line interface instead of **Fuzzy Logic Designer**. For an example, see “Build Fuzzy Systems at the Command Line” on page 2-31.

The Basic Tipping Problem

This example creates a Mamdani fuzzy inference system using on a two-input, one-output tipping problem based on tipping practices in the U.S. While the example creates a Mamdani FIS, the methods used apply to creating Sugeno systems as well.

Given a number between 0 and 10 that represents the quality of service at a restaurant (where 10 is excellent), and another number between 0 and 10 that represents the quality of the food at that restaurant (again, 10 is excellent), what should the tip be?

The starting point is to write down the three golden rules of tipping:

- 1 If the service is poor or the food is rancid, then tip is cheap.
- 2 If the service is good, then tip is average.
- 3 If the service is excellent or the food is delicious, then tip is generous.

Assume that an average tip is 15%, a generous tip is 25%, and a cheap tip is 5%.



The numbers and the shape of the curve are subject to local traditions, cultural bias, and so on, but the three rules are generally universal.


Now that you know the rules and have an idea of what the output should look like, use the UI tools to construct a fuzzy inference system for this decision process.

Fuzzy Logic Designer

The **Fuzzy Logic Designer** app displays information about a fuzzy inference system. To open **Fuzzy Logic Designer**, type the following command at the MATLAB prompt:

```
fuzzyLogicDesigner
```

Fuzzy Logic Designer opens and displays a diagram of the fuzzy inference system with the names of each input variable on the left, and those of each output variable on the right, as shown in the next figure. The sample membership functions shown in the boxes are just icons and do not depict the actual shapes of the membership functions.



Below the diagram is the name of the system and the type of inference used.

Name of the system.
To change it, select
File > Export > To Workspace.

Options for adjusting the fuzzy inference functions, such as the defuzzification method.

Status line describes the most recent operation.

Name of the selected input or output variables.

In this example, you use the default Mamdani-type inference. Another type of inference, called Sugeno-type inference, is also available. For more information, see “Mamdani and Sugeno Fuzzy Inference Systems” on page 2-2.


In **Fuzzy Logic Designer**:

- The drop-down lists let you modify the fuzzy inference functions.
- The **Current Variable** area displays the name of either an input or output variable, its type, and default range.
- A status line at the bottom displays information about the most recent operation.

To build the fuzzy inference system described in “The Basic Tipping Problem” on page 2-16 from scratch, type the following command at the MATLAB prompt:

```
fuzzyLogicDesigner
```

The generic untitled **Fuzzy Logic Designer** opens, with one input **input1**, and one output **output1**.



Tip To open **Fuzzy Logic Designer** with the prebuilt fuzzy inference system stored in `tipper.fis`, enter

```
fuzzyLogicDesigner('tipper.fis')
```

However, if you load the prebuilt system, you will not build rules or construct membership functions.

In this example, you construct a two-input, one output system. The two inputs are **service** and **food**. The one output is **tip**.


To add a second input variable and change the variable names to reflect these designations:

- 1 Select **Edit > Add variable > Input**.

A second yellow box labeled **input2** appears.


- 2 Click the yellow box **input1**. This box is highlighted with a red outline.
- 3 Edit the **Name** field from `input1` to `service`, and press **Enter**.
- 4 Click the yellow box **input2**. This box is highlighted with a red outline.
- 5 Edit the **Name** field from `input2` to `food`, and press **Enter**.

- 6 Click the blue box **output1**.
- 7 Edit the **Name** field from output1 to tip, and press **Enter**.
- 8 Select **File > Export > To Workspace**.



- 9 Enter the **Workspace variable** name tipper, and click **OK**.

The diagram is updated to reflect the new names of the input and output variables. There is now a new variable in the workspace called **tipper** that contains all the information about this system. By saving to the workspace with a new name, you also rename the entire system. Your window looks something like the following diagram.





Leave the inference options in the lower left in their default positions for now. You have entered all the information you need for this particular UI. Next, define the membership functions associated with each of the variables. To do this, open the Membership Function Editor.

You can open the Membership Function Editor in one of three ways:

- Within the **Fuzzy Logic Designer** app, select **Edit > Membership Functions**.
- Within the **Fuzzy Logic Designer** app, double-click the blue icon called **tip**.
- At the command line, type `mfedit`.

The Membership Function Editor

The Membership Function Editor is the tool that lets you display and edit all of the membership functions associated with all of the input and output variables for the entire fuzzy inference system. The Membership Function Editor shares some features with **Fuzzy Logic Designer**, as shown in the next figure. In fact, all of the five basic UI tools have similar menu options, status lines, and **Help** and **Close** buttons.



When you open the Membership Function Editor to work on a fuzzy inference system that does not already exist in the workspace, there are no membership functions associated with the variables that you defined with **Fuzzy Logic Designer**.

On the upper-left side of the graph area in the Membership Function Editor is a "Variable Palette" that lets you set the membership functions for a given variable.

To set up the membership functions associated with an input or an output variable for the FIS, select a FIS variable in this region by clicking it.


Next select the **Edit** pull-down menu, and choose **Add MFs ..** A new window appears, which allows you to select both the membership function type and the number of membership functions associated with the selected variable. In the lower-right corner of the window are the controls that let you change the name, type, and parameters (shape), of the membership function, after it is selected.

The membership functions from the current variable are displayed in the main graph. These membership functions can be manipulated in two ways. You can first use the mouse to select a particular membership function associated with a given variable quality, (such as poor, for the variable, service), and then drag the membership function from side to side. This action affects the mathematical description of the quality associated with that membership function for a given variable. The selected membership function can also be tagged for dilation or contraction by clicking on the small square drag points on the membership function, and then dragging the function with the mouse toward the *outside*, for dilation, or toward the *inside*, for contraction. This action changes the parameters associated with that membership function.


Below the Variable Palette is some information about the type and name of the current variable. There is a text field in this region that lets you change the limits of the current variable's range (universe of discourse) and another that lets you set the limits of the current plot (which has no real effect on the system).

The process of specifying the membership functions for the two-input tipping example, `tipper`, is as follows:

- 1 Double-click the input variable `service` to open the Membership Function Editor.



- 2 In the Membership Function Editor, enter [0 10] in the **Range** and the **Display Range** fields.
- 3 Create membership functions for the input variable *service*.
 - a Select **Edit > Remove All MFs** to remove the default membership functions for the input variable *service*.
 - b Select **Edit > Add MFs** to open the Membership Functions dialog box.
 - c In the Membership Functions dialog box, select **gaussmf** as the **MF Type**.




- d Verify that 3 is selected as the **Number of MFs**.
 - e Click **OK** to add three Gaussian curves to the input variable *service*.
- 4 Rename the membership functions for the input variable *service*, and specify their parameters.
 - a Click on the curve named *mf1* to select it, and specify the following fields in the **Current Membership Function (click on MF to select)** area:
 - In the **Name** field, enter *poor*.
 - In the **Params** field, enter [1.5 0].

The two inputs of **Params** represent the standard deviation and center for the Gaussian curve.

Tip To adjust the shape of the membership function, type in the desired parameters or use the mouse, as described previously.

- b Click on the curve named mf2 to select it, and specify the following fields in the **Current Membership Function (click on MF to select)** area:
 - In the **Name** field, enter good.
 - In the **Params** field, enter [1.5 5].
- c Click on the curve named mf3, and specify the following fields in the **Current Membership Function (click on MF to select)** area:
 - In the **Name** field, enter excellent.
 - In the **Params** field, enter [1.5 10].


The Membership Function Editor window looks similar to the following figure.



- 5 In the **FIS Variables** area, click the input variable **food** to select it.
- 6 Enter [0 10] in the **Range** and the **Display Range** fields.
- 7 Create the membership functions for the input variable **food**.
 - a Select **Edit > Remove All MFs** to remove the default Membership Functions for the input variable **food**.
 - b Select **Edit > Add MFs** to open the Membership Functions dialog box.


- c In the Membership Functions dialog box, select `trapmf` as the **MF Type**.
 - d Select 2 in the **Number of MFs** drop-down list.
 - e Click **OK** to add two trapezoidal curves to the input variable `food`.
- 8 Rename the membership functions for the input variable `food`, and specify their parameters:
- a In the **FIS Variables** area, click the input variable `food` to select it.
 - b Click on the curve named `mf1`, and specify the following fields in the **Current Membership Function (click on MF to select)** area:
 - In the **Name** field, enter `rancid`.
 - In the **Params** field, enter `[0 0 1 3]`.
 - c Click on the curve named `mf2` to select it, and enter `delicious` in the **Name** field.
- Reset the associated parameters if desired.
- 9 Click on the output variable `tip` to select it.
- 10 Enter `[0 30]` in the **Range** and the **Display Range** fields to cover the output range.
- The inputs ranges from 0 to 10, but the output is a tip between 5% and 25%.
- 11 Rename the default triangular membership functions for the output variable `tip`, and specify their parameters.
- a Click the curve named `mf1` to select it, and specify the following fields in the **Current Membership Function (click on MF to select)** area:
 - In the **Name** field, enter `cheap`.
 - In the **Params** field, enter `[0 5 10]`.
 - b Click the curve named `mf2` to select it, and specify the following fields in the **Current Membership Function (click on MF to select)** area:
 - In the **Name** field, enter `average`.
 - In the **Params** field, enter `[10 15 20]`.
 - c Click the curve named `mf3` to select it, and specify the following:
 - In the **Name** field, enter `generous`.
 - In the **Params** field, enter `[20 25 30]`.

The Membership Function Editor looks similar to the following figure.



Now that the variables have been named and the membership functions have appropriate shapes and names, you can enter the rules. To call up the Rule Editor, go to the **Edit** menu and select **Rules**, or type `ruleedit` at the command line.

The Rule Editor



Constructing rules using the graphical Rule Editor interface is fairly self evident. Based on the descriptions of the input and output variables defined with **Fuzzy Logic Designer**, the Rule Editor allows you to construct the rule statements automatically. You can:

- Create rules by selecting an item in each input and output variable box, selecting one **Connection** item, and clicking **Add Rule**. You can choose **none** as one of the variable qualities to exclude that variable from a given rule and choose **not** under any variable name to negate the associated quality.
- Delete a rule by selecting the rule and clicking **Delete Rule**.
- Edit a rule by changing the selection in the variable box and clicking **Change Rule**.
- Specify weight to a rule by typing in a desired number between 0 and 1 in **Weight**. If you do not specify the weight, it is assumed to be unity (1).

Similar to those in **Fuzzy Logic Designer** and the Membership Function Editor, the Rule Editor has the menu bar and the status line. The menu items allow you to open, close, save and edit a fuzzy system using the five basic UI tools. From the menu, you can also:

- Set the format for the display by selecting **Options > Format**.
- Set the language by selecting **Options > Language**.

You can access information about the Rule Editor by clicking **Help** and close the UI using **Close**.

To insert the first rule in the Rule Editor, select the following:

- **poor** under the variable **service**
- **rancid** under the variable **food**
- The **or** radio button, in the **Connection** block
- **cheap**, under the output variable, **tip**.

Then, click **Add rule**.

The resulting rule is

1. *If (service is poor) or (food is rancid) then (tip is cheap) (1)*

The numbers in the parentheses represent weights.

Follow a similar procedure to insert the second and third rules in the Rule Editor to get

- 1 *If (service is poor) or (food is rancid) then (tip is cheap) (1)*
- 2 *If (service is good) then (tip is average) (1)*
- 3 *If (service is excellent) or (food is delicious) then (tip is generous) (1)*

Tip To change a rule, first click on the rule to be changed. Next make the desired changes to that rule, and then click **Change rule**. For example, to change the first rule to

1. *If (service not poor) or (food not rancid) then (tip is not cheap) (1)*

Select the **not** check box under each variable, and then click **Change rule**.

The **Format** pop-up menu from the **Options** menu indicates that you are looking at the verbose form of the rules. Try changing it to **symbolic**. You will see

1. *(service==poor) | (food==rancid) => (tip=cheap) (1)*
2. *(service==good) => (tip=average) (1)*
3. *(service==excellent) | (food==delicious) => (tip=generous) (1)*

There is not much difference in the display really, but it is slightly more language neutral, because it does not depend on terms like *if* and *then*. If you change the format to indexed, you see an extremely compressed version of the rules.

1 1, 1 (1) : 2
2 0, 2 (1) : 1
3 2, 3 (1) : 2

This is the version of the rules that the machine deals with.

- The first column in this structure corresponds to the input variables.
- The second column corresponds to the output variable.
- The third column displays the weight applied to each rule.
- The fourth column is shorthand that indicates whether this is an OR (2) rule or an AND (1) rule.


- The numbers in the first two columns refer to the index number of the membership function.

A literal interpretation of rule 1 is "If input 1 is MF1 (the first membership function associated with input 1) or if input 2 is MF1, then output 1 should be MF1 (the first membership function associated with output 1) with the weight 1."

The symbolic format does not consider the terms, *if*, *then*, and so on. The indexed format doesn't even bother with the names of your variables. Obviously the functionality of your system doesn't depend on how well you have named your variables and membership functions. The whole point of naming variables descriptively is, as always, making the system easier for you to interpret. Thus, unless you have some special purpose in mind, it is probably be easier for you to continue with the **verbose** format.

At this point, the fuzzy inference system has been completely defined, in that the variables, membership functions, and the rules necessary to calculate tips are in place. Now, look at the fuzzy inference diagram presented at the end of the previous section and verify that everything is behaving the way you think it should. You can use the Rule Viewer, the next of the UI tools we'll look at. From the **View** menu, select **Rules**.

The Rule Viewer



The Rule Viewer displays a roadmap of the whole fuzzy inference process. It is based on the fuzzy inference diagram described in the previous section. You see a single figure window with 10 plots nested in it. The three plots across the top of the figure represent the antecedent and consequent of the first rule. Each rule is a row of plots, and each column is a variable. The rule numbers are displayed on the left of each row. You can click on a rule number to view the rule in the status line.

- The first two columns of plots (the six yellow plots) show the membership functions referenced by the antecedent, or the if-part of each rule.
- The third column of plots (the three blue plots) shows the membership functions referenced by the consequent, or the then-part of each rule.

Notice that under **food**, there is a plot which is blank. This corresponds to the characterization of none for the variable **food** in the second rule.

- The fourth plot in the third column of plots represents the aggregate weighted decision for the given inference system.

This decision will depend on the input values for the system. The defuzzified output is displayed as a bold vertical line on this plot.

The variables and their current values are displayed on top of the columns. In the lower left, there is a text field **Input** in which you can enter specific input values. For the two-input system, you will enter an input vector, [9 8], for example, and then press **Enter**. You can also adjust these input values by clicking on any of the three plots for each input. This will move the red index line horizontally, to the point where you have clicked. Alternatively, you can also click and drag this line in order to change the input values. When you release the line, (or after manually specifying the input), a new calculation is performed, and you can see the whole fuzzy inference process take place:

- Where the index line representing service crosses the membership function line "service is poor" in the upper-left plot determines the degree to which rule one is activated.
- A yellow patch of color under the actual membership function curve is used to make the fuzzy membership value visually apparent.


Each of the characterizations of each of the variables is specified with respect to the input index line in this manner. If you follow rule 1 across the top of the diagram, you can see the consequent "tip is cheap" has been truncated to exactly the same degree as the (composite) antecedent — this is the implication process in action. The aggregation occurs down the third column, and the resultant aggregate plot is shown in the single plot appearing in the lower right corner of the plot field. The defuzzified output value is shown by the thick line passing through the aggregate fuzzy set.

You can shift the plots using **left**, **right**, **down**, and **up**. The menu items allow you to save, open, or edit a fuzzy system using any of the five basic UI tools.

The Rule Viewer allows you to interpret the entire fuzzy inference process at once. The Rule Viewer also shows how the shape of certain membership functions influences the overall result. Because it plots every part of every rule, it can become unwieldy for particularly large systems, but, for a relatively small number of inputs and outputs, it performs well (depending on how much screen space you devote to it) with up to 30 rules and as many as 6 or 7 variables.

The Rule Viewer shows one calculation at a time and in great detail. In this sense, it presents a sort of micro view of the fuzzy inference system. If you want to see the entire output surface of your system — the entire span of the output set based on the entire span of the input set — you need to open up the Surface Viewer. This viewer is the last of the five basic Fuzzy Logic Toolbox UI tools. To open the Surface Viewer, select **Surface** from the **View** menu.

The Surface Viewer



Upon opening the Surface Viewer, you see a three-dimensional curve that represents the mapping from food and service quality to tip amount. Because this curve represents a two-input one-output case, you can see the entire mapping in one plot. When we move beyond three dimensions overall, we start to encounter trouble displaying the results.

Accordingly, the Surface Viewer is equipped with drop-down menus **X (input)**, **Y (input)** and **Z (output)** that let you select any two inputs and any one output for plotting. Below these menus are two input fields **X grids** and **Y grids** that let you specify how many x-axis and y-axis grid lines you want to include. This capability allows you to keep the calculation time reasonable for complex problems.

By default, the surface plot updates automatically when you change the input or output variable selections or the number of grid points. To disable automatic plot updates, in the **Options** menu, clear the **Always evaluate** option. When this option is disabled, to update the plot, click **Evaluate**.

If you want to create a smoother plot, use the **Plot points** field to specify the number of points on which the membership functions are evaluated in the input or output range. This field defaults to the minimum number of plot plots, 101. If you specify fewer plot points, the field value automatically resets to 101. When you specify the number of plot points, the surface plot automatically updates.

By clicking on the plot axes and dragging the mouse, you can manipulate the surface so that you can view it from different angles.

The **Ref. Input** field is used in situations when there are more inputs required by the system than the surface is mapping. You can edit this field to explicitly set inputs not specified in the surface plot.

Suppose you have a four-input one-output system and would like to see the output surface. The Surface Viewer can generate a three-dimensional output surface where any two of the inputs vary, but two of the inputs must be held constant because computer monitors cannot display a five-dimensional shape. In such a case, the input is a four-dimensional vector with NaNs holding the place of the varying inputs while numerical values indicates those values that remain fixed.

The menu items allow you to open, close, save and edit a fuzzy system using the five basic UI tools. You can access information about the Surface Viewer by clicking **Help** and close the UI using **Close**.

Importing and Exporting Fuzzy Inference Systems

When you save a fuzzy system to a file, you are saving an ASCII text FIS file representation of that system with the file suffix `.fis`. Do not manually edit the contents of a `.fis` file. Doing so can produce unexpected results when loading the file. When you save your fuzzy system to the MATLAB workspace, you are creating a variable that acts as a MATLAB object for the fuzzy system.

Note If you do not save your FIS to a file, but only save it to the MATLAB workspace, you cannot recover it for use in a new MATLAB session.

See Also

Fuzzy Logic Designer

More About

- “Build Fuzzy Systems at the Command Line” on page 2-31
- “Simulate Fuzzy Inference Systems in Simulink” on page 5-2

Build Fuzzy Systems at the Command Line

You can construct a fuzzy inference system (FIS) at the MATLAB® command line. This method is an alternative to interactively designing your FIS using Fuzzy Logic Designer.

This example shows you how to create a Mamdani fuzzy inference system. While you create a Mamdani FIS, the methods used apply to creating Sugeno systems as well.

Tipping Problem at the Command Line

To demonstrate the command-line functionality for creating and viewing fuzzy inference systems, this example uses the tipper FIS.

```
fis = readfis('tipper.fis');
```

This command returns a `mamfis` object that contains the properties of the fuzzy system. For a Sugeno system, this command returns a `sugfis` object.

You can access the FIS properties using dot notation. For example, view the inputs of the fuzzy system.

```
fis.Inputs
```

```
ans =  
1x2 fisvar array with properties:
```

```
    Name  
    Range  
    MembershipFunctions
```

```
Details:
```

	Name	Range	MembershipFunctions
1	"service"	0 10	{1x3 fismf}
2	"food"	0 10	{1x2 fismf}

To set the properties of your fuzzy system, use dot notation. For example, set the name of the FIS.

```
fis.Name = "gratuity";
```

FIS Object

You represent fuzzy inference systems using `mamfis` and `sugfis` objects. These objects contain all the fuzzy inference system information, including the variable names, membership function definitions, and fuzzy inference methods. Each FIS is itself a hierarchy of objects. The following objects are used within a fuzzy system:

- `fisvar` objects represent both input and output variables.
- `fismf` objects represent membership functions within each input and output variable.
- `fisrule` objects represent fuzzy rules that map inputs to outputs.

View all the information for a FIS by directly listing its properties.

```
fis
```

```

fis =
  mamfis with properties:

                Name: "gratuity"
            AndMethod: "min"
            OrMethod: "max"
    ImplicationMethod: "min"
    AggregationMethod: "max"
    DefuzzificationMethod: "centroid"
                Inputs: [1x2 fisvar]
                Outputs: [1x1 fisvar]
                Rules: [1x3 fisrule]
    DisableStructuralChecks: 0

    See 'getTunableSettings' method for parameter optimization.
  
```

You can view the properties of the objects within a FIS object using dot notation. For example, view the `fisvar` object for first input variable.

```

fis.Inputs(1)

ans =
  fisvar with properties:

                Name: "service"
                Range: [0 10]
    MembershipFunctions: [1x3 fismf]
  
```

Also, view the membership functions for this variable.

```

fis.Inputs(1).MembershipFunctions

ans =
  1x3 fismf array with properties:

    Type
    Parameters
    Name

    Details:


```

	Name	Type	Parameters
1	"poor"	"gaussmf"	1.5 0
2	"good"	"gaussmf"	1.5 5
3	"excellent"	"gaussmf"	1.5 10

System Display Functions

To get a high-level view of your fuzzy system from the command line, use the `plotfis`, `plotmf`, and `gensurf` functions. `plotfis` displays the whole system as a block diagram, as shown in the **Fuzzy Logic Designer**.


```
plotfis(fis)
```



System gratuity: 2 inputs, 1 outputs, 3 rules


The `plotmf` function plots all the membership functions associated with a given variable. For example, view the membership functions for the first input variable.

```
plotmf(fis, 'input', 1)
```



Similarly, to view the membership functions for the first output, type:

```
plotmf(fis, 'output', 1)
```



`plotmf` does not support viewing the output membership functions for Sugeno systems.

To view the rules of the fuzzy system, type:

```
fis.Rules
```

```
ans =
```

```
1x3 fisrule array with properties:
```

```
Description
Antecedent
Consequent
Weight
Connection
```


```
Details:
```

```
Description
```

```
1 "service==poor | food==rancid => tip=cheap (1)"
2 "service==good => tip=average (1)"
3 "service==excellent | food==delicious => tip=generous (1)"
```

The `gensurf` function plots the output of the FIS for any one or two input variables.

```
gensurf(fis)
```



Build Fuzzy Inference System

As an alternative to using the **Fuzzy Logic Designer** app, you can construct a FIS entirely from the command line.

First, create a Mamdani FIS, specifying its name.

```
fis = mamfis('Name','tipper');
```

Add the first input variable for the service quality using `addInput`.

```
fis = addInput(fis,[0 10],'Name','service');
```

Add membership functions for each of the service quality levels using `addMF`. In this case, use Gaussian membership functions. For more information on Gaussian membership function properties, see `gaussmf`.

```
fis = addMF(fis,"service","gaussmf",[1.5 0],'Name',"poor");
fis = addMF(fis,"service","gaussmf",[1.5 5],'Name',"good");
fis = addMF(fis,"service","gaussmf",[1.5 10],'Name',"excellent");
```

Add the second input variable for the food quality, and add two trapezoidal membership functions. For information on trapezoidal membership functions, see `trapmf`.

```
fis = addInput(fis,[0 10],'Name',"food");
fis = addMF(fis,"food","trapmf",[-2 0 1 3],'Name',"rancid");
fis = addMF(fis,"food","trapmf",[7 9 10 12],'Name',"delicious");
```

Add the output variable for the tip, and add three triangular membership functions. For more information on the triangular membership function, see `trimf`.

```

fis = addOutput(fis,[0 30], 'Name', "tip");
fis = addMF(fis, "tip", "trimf", [0 5 10], 'Name', "cheap");
fis = addMF(fis, "tip", "trimf", [10 15 20], 'Name', "average");
fis = addMF(fis, "tip", "trimf", [20 25 30], 'Name', "generous");

```

Specify the following three rules for the FIS as a numeric array:

- 1 If (service is poor) or (food is rancid), then (tip is cheap).
- 2 If (service is good), then (tip is average).
- 3 If (service is excellent) or (food is delicious), then (tip is generous).

Each row of the array contains one rule in the following format.

- Column 1 - Index of membership function for first input
- Column 2 - Index of membership function for second input
- Column 3 - Index of membership function for output
- Column 4 - Rule weight (from 0 to 1)
- Column 5 - Fuzzy operator (1 for AND, 2 for OR)

For the membership function indices, indicate a NOT condition using a negative value. For more information on fuzzy rule specification, see `addRule`.

```

ruleList = [1 1 1 1 2;
            2 0 2 1 1;
            3 2 3 1 2];

```

Add the rules to the FIS.

```

fis = addRule(fis, ruleList);

```

Alternatively, you can create the fuzzy inference system using a combination of dot notation and `fisvar`, `fismf`, and `fisrule` objects. This method is not a good practice for most applications. However, you can use this approach when your application requires greater flexibility in constructing and modifying your FIS.

Create the fuzzy inference system.

```

fis = mamfis('Name', 'tipper');

```

Add and configure the first input variable. In this case, create a default `fisvar` object and specify its properties using dot notation.

```

fis.Inputs(1) = fisvar;
fis.Inputs(1).Name = "service";
fis.Inputs(1).Range = [0 10];

```

Define the membership functions for the first input variable. For each MF, create a `fismf` object, and set the properties using dot notation.

```

fis.Inputs(1).MembershipFunctions(1) = fismf;
fis.Inputs(1).MembershipFunctions(1).Name = "poor";
fis.Inputs(1).MembershipFunctions(1).Type = "gaussmf";

```

```
fis.Inputs(1).MembershipFunctions(1).Parameters = [1.5 0];
fis.Inputs(1).MembershipFunctions(2) = fismf;
fis.Inputs(1).MembershipFunctions(2).Name = "good";
fis.Inputs(1).MembershipFunctions(2).Type = "gaussmf";
fis.Inputs(1).MembershipFunctions(2).Parameters = [1.5 5];
fis.Inputs(1).MembershipFunctions(3) = fismf;
fis.Inputs(1).MembershipFunctions(3).Name = "excellent";
fis.Inputs(1).MembershipFunctions(3).Type = "gaussmf";
fis.Inputs(1).MembershipFunctions(3).Parameters = [1.5 10];
```

Add and configure the second input variable. For this variable, specify the name and range when you create the `fisvar` object.

```
fis.Inputs(2) = fisvar([0 10], 'Name', "food");
```

Specify the membership functions for the second input. For each MF, specify the name, type, and parameters when you create the `fismf` object.

```
fis.Inputs(2).MembershipFunctions(1) = fismf("trapmf",[-2 0 1 3],...
                                           'Name',"rancid");
fis.Inputs(2).MembershipFunctions(2) = fismf("trapmf",[7 9 10 12],...
                                           'Name',"delicious");
```

Similarly, add and configure the output variable and its membership functions.

```
fis.Outputs(1) = fisvar([0 30], 'Name', "tip");
```

In this case, specify the output membership functions using a vector of `fismf` objects.

```
mf1 = fismf("trimf",[0 5 10], 'Name', "cheap");
mf2 = fismf("trimf",[10 15 20], 'Name', "average");
mf3 = fismf("trimf",[20 25 30], 'Name', "generous");
fis.Outputs(1).MembershipFunctions = [mf1 mf2 mf3];
```

Create the rules for the fuzzy system. For each rule create a `fisrule` object. Then, specify the rules using a vector of these objects. When creating a `fisrule` object using numeric values, you must specify the number of inputs variables.

```
rule1 = fisrule([1 1 1 1 2],2);
rule2 = fisrule([2 0 2 1 1],2);
rule3 = fisrule([3 2 3 1 2],2);
rules = [rule1 rule2 rule3];
```

Before adding your rules to your fuzzy system, you must update them using the data in the FIS object. Update the rules using the `update` function, and add them the fuzzy system.

```
rules = update(rules, fis);
fis.Rules = rules;
```

When constructing your fuzzy system, you can also specify custom membership functions and inference functions. For more information, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

Evaluate Fuzzy Inference System

To evaluate the output of a fuzzy system for a given input combination, use the `evalfis` command. For example, evaluate `fis` using input variable values of 1 and 2.


```
evalfis(fis,[1 2])
```

```
ans = 5.5586
```

You can also evaluate multiple input combinations using an array where each row represents one input combination.

```
inputs = [3 5;  
          2 7;  
          3 1];  
evalfis(fis,inputs)
```

```
ans = 3×1
```

```
12.2184  
 7.7885  
 8.9547
```

See Also

mamfis | sugfis | plotfis | plotmf | gensurf | evalfis

More About

- “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14

Build Fuzzy Systems Using Custom Functions

Build Fuzzy Inference Systems Using Custom Functions in Fuzzy Logic Designer

When you build a fuzzy inference system, as described in “Fuzzy Inference Process” on page 1-19, you can replace the built-in membership functions, inference functions, or both with custom functions. In this section, you learn how to build a fuzzy inference system using custom functions in the **Fuzzy Logic Designer** app.

To build a fuzzy inference system using custom functions in the **Fuzzy Logic Designer** app:

- 1** Open **Fuzzy Logic Designer**. At the MATLAB command line, type the following command.

```
fuzzyLogicDesigner
```
- 2** Specify the number of inputs and outputs of the fuzzy system, as described in “Fuzzy Logic Designer” on page 2-16.
- 3** Create custom membership functions, and replace the built-in membership functions with them, as described in “Specify Custom Membership Functions” on page 2-41.

Membership functions define how each point in the input space is mapped to a membership value between 0 and 1.


- 4** Create rules using the Rule Editor, as described in “The Rule Editor” on page 2-25.

Rules define the logical relationship between the inputs and the outputs.

- 5** Create custom inference functions, and replace the built-in inference functions with them, as described in “Specify Custom Inference Functions” on page 2-45.

Inference methods include the AND, OR, implication, aggregation, and defuzzification methods. This action generates the output values for the fuzzy system.

The next figure shows the tipping problem example where the built-in **Implication**, **Aggregation** and **Defuzzification** functions are replaced with the custom functions, `customimp`, `customagg`, and `customdefuzz`, respectively.



- 6 Select **View > Surface** to view the output of the fuzzy inference system in the Surface Viewer, as described in “The Surface Viewer” on page 2-29.

Specify Custom Membership Functions

You can create custom membership functions and use them in the fuzzy inference process. The values of these functions must lie between 0 and 1. For more information on the properties of membership functions, see “Membership Functions” on page 1-9.

To create a custom membership function, and replace the built-in membership function:

- 1 Create a MATLAB function, and save it in your current working folder.

To learn how to create MATLAB functions, see “Scripts vs. Functions”.

The following code is an example of a multistep custom membership function, `custmf1`, that depends on eight parameters between 0 and 10.

```
% Function to generate a multi-step custom membership function
% using 8 parameters for the input argument x
function out = custmf1(x,params)

for i = 1:length(x)
    if x(i) < params(1)
        y(i) = params(1);
    elseif x(i) < params(2)
        y(i) = params(2);
    elseif x(i) < params(3)
        y(i) = params(3);
    end
end
```

```

elseif x(i) < params(4)
    y(i) = params(4);
elseif x(i) < params(5)
    y(i) = params(5);
elseif x(i) < params(6)
    y(i) = params(6);
elseif x(i) < params(7)
    y(i) = params(7);
elseif x(i) < params(8)
    y(i) = params(8);
else
    y(i) = 0;
end
end

out = 0.1*y'; % Scale the output to lie between 0 and 1.

end

```


- Open the **Fuzzy Logic Designer** app.

fuzzyLogicDesigner


Fuzzy Logic Designer opens with the default FIS name, *Untitled*, and contains one input, **input1**, and one output, **output1**.

- In **Fuzzy Logic Designer**, select **Edit > Membership Functions** to open the Membership Function Editor.

Three triangular-shaped membership functions for **input1** are displayed by default.



- 4 To replace the default membership function with a custom function in the Membership Function Editor:
 - a Select **Edit > Remove All MFs** to remove the default membership functions for **input1**.
 - b Select **Edit > Add Custom MF** to open the Custom Membership Function dialog box.



- 5 To specify a custom function, in the Custom Membership Function dialog box:
 - a In the **MF name** field, specify a name for the custom membership function. For this example, use the name `customMF1`


Note When adding additional custom membership functions, specify a different **MF name** for each function.

- b In the **M-file function name** field, specify the name of the custom membership function file.
- c In the **Parameter list**, specify the vector of parameters. For this example use the vector `[0 1 2 4 6 8 9 10]`.

These values determine the shape and position of the membership function, and the function is evaluated using these parameter values.


Note The length of the parameter vector must be greater than or equal to the number of parameters in the custom membership function.

Using the `custmf1` example in step 1, the Custom Membership Function dialog box looks similar to the following figure.




- d Click **OK** to add the custom membership function.
- e Specify both the **Range** and **Display Range** to be [0 10] to match the range of the custom membership function.

The Membership Function Editor displays the custom membership function plot.



This action also adds the custom membership function to the Rule Viewer, and makes it available for creating rules for the fuzzy inference process. To view the custom function in the Rule Viewer, select **Edit > Rules** in either **Fuzzy Logic Designer** or the Membership Function Editor.



- 6 To add custom membership functions for **output1**, select it in the Membership Function Editor, and repeat steps 4 and 5.

You can also add a custom membership function to a FIS at the MATLAB command line. For example, to add `custmf1` to the first input variable, `input1` of the FIS, `myFIS`, and name it `customMF1`, type the following:

```
myFIS = addMF(myFIS, "input1", "custmf1", [0 1 2 4 6 8 9 10], 'Name', "customMF1");
```

Specify Custom Inference Functions

You can replace the built-in AND, OR, implication, aggregation, and defuzzification inference methods with custom functions. After you create the custom inference function, save it in your current working folder. To learn how to build fuzzy systems using custom inference functions, see the “Build Fuzzy Inference Systems Using Custom Functions in Fuzzy Logic Designer” on page 2-40 section.

The guidelines for creating and specifying the functions for building fuzzy inference systems are described in the following sections.

- “Create Custom AND and OR Functions” on page 2-46
- “Create Custom Implication Functions” on page 2-46
- “Create Custom Aggregation Functions” on page 2-47
- “Create Custom Defuzzification Functions” on page 2-48
- “Specify Custom Inference Functions in Fuzzy Inference System” on page 2-48

Create Custom AND and OR Functions

The custom AND and OR inference functions must operate column-wise on a matrix, in the same way as the MATLAB functions `max`, `min`, or `prod`.

For a row or column vector x , `min(x)` returns the minimum element.

```
x = [1 2 3 4];  
min(x)
```

```
ans =  
    1
```

For a matrix x , `min(x)` returns a row vector containing the minimum element from each column.

```
x = [1 2 3 4;5 6 7 8;9 10 11 12];  
min(x)
```

```
ans =  
    1     2     3     4
```

For N-D arrays, `min(x)` operates along the first non-singleton dimension.

The function `min(x,y)` returns an array that is same size as x and y with the minimum elements from x or y . Either of the input arguments can be a scalar. Functions such as `max`, and `prod` operate in a similar manner.

In the toolbox, the AND implication methods perform an element by element matrix operation, similar to the MATLAB function `min(x,y)`.

```
a = [1 2; 3 4];  
b = [2 2; 2 2];  
min(a,b)
```

```
ans =  
    1     2  
    2     2
```

The OR implication methods perform an element by element matrix operation, similar to the MATLAB function `max(x,y)`.

Create Custom Implication Functions

Custom implication functions must operate in the same way as the MATLAB functions `max`, `min`, or `prod`. Your custom implication function must be a T -norm fuzzy intersection operation. For more information, see “Additional Fuzzy Operators” on page 1-14.

An implication function must support either one or two inputs because the software calls the function in two ways:

- To calculate the output fuzzy set values using the firing strength of all the rules and the corresponding output membership functions. In this case, the software calls the implication function using two inputs, similar to the following example:

```
impvals = customimp(w,outputmf)
```

- w — Firing strength of multiple rules, specified as an nr -by- ns matrix. Here, nr is the number of rules and ns is the number of samples of the output membership functions.

$w(:,j) = w(:,1)$ for all j . $w(i,1)$ is the firing strength of the i^{th} rule.

- **outputmf** — Output membership function values, specified as an nr -by- ns matrix. Here, nr is the number of rules and ns is the number of samples of the output membership functions.

`outputmf(i,:)` contains the data of the i^{th} output membership function.

- To calculate the output fuzzy value using the firing strength of a single rule and the corresponding output membership function, for a given sample. In this case, the software calls the implication function using one input, similar to the following example:

```
impval = customimp([w outputmf])
```

w and `outputmf` are scalar values representing the firing strength of a rule and the corresponding output membership function value, for a given sample.

The following is an example of a bounded product custom implication function with binary mapping $T(a,b) = \max\{0, a + b - 1\}$. [1]

```
function y = customimp(x1,x2)

if nargin == 1
    % x1 assumed to be non-empty column vector or matrix.
    minVal = zeros(1,size(x1,2));
    y = ones(1,size(x1,2));

    for i = 1:size(x1,1)
        y = max(minVal,sum([y;x1(i,:)])-1);
    end
else
    % x1 and x2 assumed to be non-empty matrices.
    minVal = zeros(1,size(x1,2));
    y = zeros(size(x1));

    for i = 1:size(x1,1)
        y(i,:) = max(minVal,sum([x1(i,:);x2(i,:)])-1);
    end
end

end

end
```

Note Custom implication functions are not supported for Sugeno-type systems.

Create Custom Aggregation Functions

The custom aggregation functions must operate in the same way as the MATLAB functions `max`, `min`, or `prod` and must be of the form $y = \text{customagg}(x)$. Your custom implication function must be a T -conorm (S -norm) fuzzy intersection operation. For more information, see “Additional Fuzzy Operators” on page 1-14.

x is an nv -by- nr matrix, which is the list of truncated output functions returned by the implication method for each rule. nv is the number of output variables, and nr is the number of rules. The output of the aggregation method is one fuzzy set for each output variable.

The following is an example of a bounded sum custom aggregation function with binary mapping $S(a,b) = \min\{a + b, 1\}$. [1]

```
function y = customagg(x)

maxVal = ones(1,size(x,2));
y = zeros(1,size(x,2));

for i = 1:size(x,1)
    y = min(maxVal,sum([y;x(i,:) ]));
end

end
```

Note Custom aggregation functions are not supported for Sugeno-type systems.

Create Custom Defuzzification Functions

The custom defuzzification functions must be of the form `y = customdefuzz(x,ymf)`, where `x` is the vector of values in the membership function input range, and `ymf` contains the values of the membership function for each `x` value.

The following is an example of a custom defuzzification function:

```
function defuzzfun = customdefuzz(x,ymf)

total_area = sum(ymf);
defuzzfun = sum(ymf.*x)/total_area;

end
```

Note Custom defuzzification functions are not supported for Sugeno-type systems.


Specify Custom Inference Functions in Fuzzy Inference System

After you create and save a custom inference function, you can specify the function in the fuzzy inference system at the command line or using **Fuzzy Logic Designer**.

To specify custom inference functions in **Fuzzy Logic Designer**, use the following steps.


Note In order to specify a custom inference function in **Fuzzy Logic Designer**, you must first add at least one rule to your FIS.

- 1 In the lower-left panel of **Fuzzy Logic Designer**, select **Custom** from the drop-down menu corresponding to the inference method for which you want to specify the custom function.



Doing so opens a dialog box where you specify the name of the custom inference function.

- 2 In the **Method name** field, specify the name of the custom inference function, and click **OK**.



The custom function replaces the built-in function when building the fuzzy inference system.

- 3 To specify custom functions for other inference methods, repeat steps 1 and 2.

To specify custom inference functions for a FIS (myFIS) at the MATLAB command line, set the corresponding FIS object property to the inference function name. For example, to add a custom:

- Defuzzification method, type

```
myFIS.DefuzzificationMethod = "customdefuzz";
```

where customdefuzz is the name of the custom defuzzification function.

- Implication method, type

```
myFIS.ImplicationMethod = "customimp";
```

where `customimp` is the name of the custom implication function.

- Aggregation method, type

```
myFIS.AggregationMethod = "customagg";
```

where `customagg` is the name of the custom aggregation function.

Specify Custom Type-Reduction Functions

For type-2 fuzzy inference systems, you can specify a custom type-reduction function. This function must be of the form $y = \text{customtr}(x, \text{umf}, \text{l mf})$, where x is the vector of values in the membership function input range. `umf` and `l mf` are the respective values of the upper and lower membership function for each x value. The output y is a two-element row vector of centroids $[c_L, c_R]$.

For more information on type reduction, see “Type-2 Fuzzy Inference Systems” on page 2-7.

By default, type-2 Sugeno systems support only a weighted average form of type reduction. The following custom type-reduction function implements a weighted sum form of type reduction for a Sugeno system.

```
function y = customtr(x,umf,ymf)
```

```
y = zeros(1,2);
```

```
y(1) = sum(x.*umf);
```

```
y(2) = sum(x.*ymf);
```

```
end
```

To specify the custom type-reduction function for a FIS (`myFIS`) at the MATLAB command line, type

```
myFIS.DTypeReductionMethod = "customtr";
```

where `customtr` is the name of the custom defuzzification function.

Use Custom Functions in Code Generation

You can use custom functions in fuzzy inference systems for which you generate code. For more information on code generation for fuzzy systems, see “Deploy Fuzzy Inference Systems” on page 6-2.

If you use a nondouble data type for your generated code, you must propagate the data type from the input arguments of your custom function to the output argument. For example, the following custom aggregation function maintains the data type of x in y using the `ones` and `zeros` with the `'like'` argument.

```
function y = customagg(x)
```

```
maxVal = ones(1,size(x,2),'like',x);
```

```
y = zeros(1,size(x,2),'like',x);
```

```
for i = 1:size(x,1)
```

```
    y = min(maxVal,sum([y;x(i,:)]));
```

```
end
```

end

For more information on writing functions that support C/C++ code generation, see “MATLAB Programming for Code Generation” (MATLAB Coder).

References

- [1] Mizumoto, Masaharu. ‘Pictorial Representations of Fuzzy Connectives, Part II: Cases of Compensatory Operators and Self-Dual Operators’. *Fuzzy Sets and Systems* 32, no. 1 (August 1989): 45-79. [https://doi.org/10.1016/0165-0114\(89\)90087-0](https://doi.org/10.1016/0165-0114(89)90087-0).

See Also

Fuzzy Logic Designer

Related Examples

- “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14
- “Build Fuzzy Systems at the Command Line” on page 2-31


Fuzzy Trees

As the number of inputs to a fuzzy system increases, the number of rules increases exponentially. This large rule base reduces the computational efficiency of the fuzzy system. It also makes the operation of the fuzzy system harder to understand, and it makes the tuning of rule and membership function parameters more difficult. Because many applications have a limited amount of training data, a large rule base reduces the generalizability of tuned fuzzy systems.

To overcome this issue, you can implement a fuzzy inference system (FIS) as a tree of smaller interconnected FIS objects rather than as a single monolithic FIS object. These fuzzy trees are also known as hierarchical fuzzy systems because the fuzzy systems are arranged in hierarchical tree structures. In a tree structure, the outputs of the low-level fuzzy systems are used as inputs to the high-level fuzzy systems. A fuzzy tree is more computationally efficient and easier to understand than a single FIS with the same number of inputs.

Types of Hierarchical Structures

There are several fuzzy tree structures that you can use for your application. The following figure shows commonly used fuzzy tree structures: an incremental, aggregated, or cascaded structure.




Incremental Structure

In an incremental structure, input values are incorporated in multiple stages to refine the output values in several levels. For example, the previous figure shows a three-level incremental fuzzy tree having fuzzy inference systems FIS_i^n , where i indicates the index of a FIS in the n th level. In an incremental fuzzy tree, $i = 1$, meaning that each level has only one fuzzy inference system. In the previous figure, the j th input of the i th FIS in the n th level is shown as input x_{ij}^n , whereas the k th output of the i th FIS in the n th level is shown as output y_{ik}^n . In the figure, $n = 3$, $j = 1$ or 2 , and $k = 1$.

If each input has m membership functions (MFs), each FIS has a complete set of m^2 rules. Hence, the total number of rules is $nm^2 = 3 \times 3^2 = 27$.


The following figure shows a monolithic ($n = 1$) FIS with four inputs ($j=1, 2, 3, 4$) and three MFs ($m = 3$).



In the FIS of this figure, the total number of rules is $nm^4 = 1 \times 3^4 = 81$. Hence, the total number of rules in an incremental fuzzy tree is linear with the number of input pairs.

Input selection at different levels in an incremental fuzzy tree uses input rankings based on their contributions to the final output values. The input values that contribute the most are generally used at the lowest level, while the least influential ones are used at the highest level. In other words, low-rank input values are dependent on high-rank input values.


In an incremental fuzzy tree, each input value usually contributes to the inference process to a certain extent, without being significantly correlated with the other inputs. For example, a fuzzy system forecasts the possibility of buying an automobile using four inputs: color, number of doors, horse power, and autopilot. The inputs are four distinct automobile features, which can independently influence a buyer's decision. Hence, the inputs can be ranked using the existing data to construct a fuzzy tree, as shown in the following figure.



For an example that illustrates creating an incremental fuzzy tree in MATLAB, see the "Create Incremental FIS Tree" example on the `fistree` reference page.


Aggregated Structure

In an aggregated structure, input values are incorporated as groups at the lowest level, where each input group is fed into a FIS. The outputs of the lower level fuzzy systems are combined (aggregated) using the higher level fuzzy systems. For example, the following shows a two-level aggregated fuzzy tree having fuzzy inference systems $FIS_{i_n}^n$, where i_n indicates the index of a FIS in the n th level.



In this aggregated fuzzy tree, $i_1 = 1, 2$ and $i_2 = 1$. Hence, each level includes a different number of FIS. The j th input of the i_n th FIS is shown in the figure as input $x_{i_n j}$, and the k th output of the i_n th FIS is shown as output $y_{i_n k}$. In the figure, $j = 1, 2$ and $k = 1$. In other words, each FIS has two inputs and one output. If each input has m MFs, then each FIS has a complete set of m^2 rules. Hence, the total number of rules for the three fuzzy systems is $3 m^2 = 3 \times 32 = 27$, which is the same as an incremental FIS for a similar configuration.

In an aggregated fuzzy tree, input values are naturally grouped together for specific decision-making. For example, an autonomous robot navigation task combines obstacle avoidance and target reaching subtasks for collision-free navigation. To achieve the navigation task, the fuzzy tree can use four inputs: distance to the closest obstacle, angle of the closest obstacle, distance to the target, and angle of the target. Distances and angles are measured with respect to the current position and heading direction of the robot. In this case, at the lowest level, the inputs naturally group as shown in the following figure: obstacle distance and obstacle angle (group 1) and target distance and target angle (group 2). Two fuzzy systems separately process individual group inputs and then another fuzzy system combines their outputs to produce a collision-free heading for the robot.




For an example that illustrates creating an aggregated fuzzy tree in MATLAB, see the example Create Aggregated FIS Tree on the `fistree` reference page.

Variation on Aggregated Structure

In a variation of the aggregated structure known as parallel structure [1], the outputs of the lowest-level fuzzy systems are directly summed to generate the final output value. The following figure


shows an example of a parallel fuzzy tree, where outputs of `fis1` and `fis2` are summed to produce the final output.



The `fistree` object does not provide the summing node Σ . Therefore, you must add a custom aggregation method to evaluate a parallel fuzzy tree. For an example, see the "Create and Evaluate Parallel FIS Tree" example on the `fistree` reference page.


Cascaded or Combined Structure

A cascaded structure, also known as combined structure, combines both incremental and aggregated structures to construct a fuzzy tree. This structure is suitable for a system that includes both correlated and uncorrelated inputs. The tree groups the correlated inputs in an aggregated structure, and adds uncorrelated inputs in an incremental structure. The following figure shows an example of a cascaded tree structure, where the first four inputs are grouped pairwise in an aggregated structure and the fifth input is added in an incremental structure.



Cascaded (combined)


For example, consider the robot navigation task discussed in “Aggregated Structure” on page 2-53. Suppose that task includes another input, the previous heading of the robot, taken into account to prevent large changes in the robot heading. You can add this input using the incremental structure of the following diagram.



For an example that illustrates creating an aggregated fuzzy tree in MATLAB, see the "Create Cascaded FIS Tree" example on the `fistree` reference page.

Add or Remove FIS Tree Outputs


When you evaluate a `fistree` object, it returns results for only the open outputs, which are not connected to any FIS inputs in the fuzzy tree. You can optionally access other outputs in the tree. For instance, in the following diagram of an aggregated fuzzy tree, you might want to obtain the output of `fis2` when you evaluate the tree.



You can add such outputs to a `fistree` object. You can also remove outputs, provided that the fuzzy tree always has at least one output. For an example, see the "Update FIS Tree Outputs" example on the `fistree` reference page.

Use the Same Value for Multiple inputs of FIS Tree

A `fistree` object allows using the same value for multiple inputs. For instance, in the following figure, `input2` of `fis1` and `input1` of `fis2` use the same value during evaluation.



For an example showing how to construct a FIS tree in this way, see the "Use Same Value for Multiple Inputs of a FIS Tree" example on the `fistree` reference page.

Update Fuzzy Inference Systems in FIS Tree

You can add or remove individual FIS elements from a `fistree` object. When you do so, the software automatically updates the `Connections`, `Inputs`, and `Outputs` properties of the `fistree` object. For an example, see the "Update Fuzzy Inference Systems in a FIS Tree" example on the `fistree` reference page.

Tune a Fuzzy Tree

Once you have configured the internal connections in your fuzzy tree, the next step is to tune the parameters of the tree. For an example, see "Tune FIS Tree for Gas Mileage Prediction" on page 3-38.

References

- [1] Siddique, Nazmul, and Hojjat Adeli. *Computational Intelligence: Synergies of Fuzzy Logic, Neural Networks and Evolutionary Computing*. Oxford, UK: John Wiley & Sons Ltd, 2013. <https://doi.org/10.1002/9781118534823>.

See Also

`fistree`

More About


- "Tuning Fuzzy Inference Systems" on page 3-2
- "Tune FIS Tree for Gas Mileage Prediction" on page 3-38

Fuzzy PID Control with Type-2 FIS

This example compares a type-2 fuzzy PID controller with both a type-1 fuzzy PID controller and conventional PID controller. This example is adapted from [1].

Fuzzy PID Control

This example uses the following fuzzy logic controller (FLC) structure as described in [1]. The output of the controller (u) is found using the error (e) and the derivative of the error (\dot{e}). Using scaling factors C_e and C_d , inputs e and \dot{e} are normalized to E and ΔE , respectively. The normalized ranges for both inputs are in the range $[-1,1]$. The fuzzy logic controller also produces a normalized output in the range $[-1,1]$. Additional scaling factors C_0 and C_1 map the fuzzy logic controller output U into u .



This example uses a delayed first-order system $G(s)$ as the plant model.

$$G(s) = \frac{Ce^{-Ls}}{Ts + 1}$$

Here, C , L , and T are the gain, time delay, and time constant, respectively.

The scaling factors C_d , C_0 , and C_1 are defined as follows, where τ_c is the closed-loop time constant.

$$C_d = \min\left(T, \frac{L}{2}\right) \times C_e$$

$$C_0 = \frac{1}{C \times C_e \left(\tau_c + \frac{L}{2}\right)}$$

$$C_1 = \max\left(T, \frac{L}{2}\right) \times C_0$$

The input scaling factor C_e is:

$$C_e \equiv \frac{1}{r(t_r) - y(t_r)}$$

where $r(t_r)$ and $y(t_r)$ are the reference and system output values at time $t = t_r$. These values correspond to the nominal operating point of the system.

This example compares the performance of type-1 and type-2 Sugeno fuzzy inference systems (FISs) using the Fuzzy Logic Controller Simulink® block.

Construct Type-1 FIS

Create a type-1 FIS using `sugfis`.

```
fis1 = sugfis;
```

Add input variables to the FIS.


```
fis1 = addInput(fis1,[-1 1], 'Name', 'E');
fis1 = addInput(fis1,[-1 1], 'Name', 'delE');
```

Add three uniformly distributed overlapping triangular membership functions (MFs) to each input. The MF names stand for *negative* (N), *zero* (Z), and *positive* (P).

```
fis1 = addMF(fis1, 'E', 'trimf', [-2 -1 0], 'Name', 'N');
fis1 = addMF(fis1, 'E', 'trimf', [-1 0 1], 'Name', 'Z');
fis1 = addMF(fis1, 'E', 'trimf', [0 1 2], 'Name', 'P');
fis1 = addMF(fis1, 'delE', 'trimf', [-2 -1 0], 'Name', 'N');
fis1 = addMF(fis1, 'delE', 'trimf', [-1 0 1], 'Name', 'Z');
fis1 = addMF(fis1, 'delE', 'trimf', [0 1 2], 'Name', 'P');
```

Plot the input membership functions.

```
figure
subplot(1,2,1)
plotmf(fis1, 'input', 1)
title('Input 1')
subplot(1,2,2)
plotmf(fis1, 'input', 2)
title('Input 2')
```



Add the output variable to the FIS.

```
fis1 = addOutput(fis1,[-1 1], 'Name', 'U');
```

Add uniformly distributed constant functions to the output. The MF names stand for *negative big* (NB), *negative medium* (NM), *zero* (Z), *positive medium* (PM), and *positive big* (PB).


```
fis1 = addMF(fis1,'U','constant',-1,'Name','NB');
fis1 = addMF(fis1,'U','constant',-0.5,'Name','NM');
fis1 = addMF(fis1,'U','constant',0,'Name','Z');
fis1 = addMF(fis1,'U','constant',0.5,'Name','PM');
fis1 = addMF(fis1,'U','constant',1,'Name','PB');
```

Add rules to the FIS. These rules create a proportional control surface.

```
rules = [...
    "E==N & delE==N => U=NB"; ...
    "E==Z & delE==N => U=NM"; ...
    "E==P & delE==N => U=Z"; ...
    "E==N & delE==Z => U=NM"; ...
    "E==Z & delE==Z => U=Z"; ...
    "E==P & delE==Z => U=PM"; ...
    "E==N & delE==P => U=Z"; ...
    "E==Z & delE==P => U=PM"; ...
    "E==P & delE==P => U=PB" ...
];
fis1 = addRule(fis1,rules);
```

Plot the control surface.

```
figure
gensurf(fis1)
title('Control surface of type-1 FIS')
```



Construct Type-2 FIS

Convert the type-1 FIS, `fis1`, to a type-2 FIS.

```
fis2 = convertToType2(fis1);
```


The type-2 Sugeno system, `fis2`, uses type-2 membership functions for the input variables and type-1 membership functions for the output variables.

Define the footprint of uncertainty (FOU) for the input MFs as defined in [1]. To do so, set the lower MF scaling factor for each MF. For this example, set the lower MF lag values to 0.

```
scale = [0.2 0.9 0.2; 0.3 0.9 0.3];
for i = 1:length(fis2.Inputs)
    for j = 1:length(fis2.Inputs(i).MembershipFunctions)
        fis2.Inputs(i).MembershipFunctions(j).LowerLag = 0;
        fis2.Inputs(i).MembershipFunctions(j).LowerScale = scale(i,j);
    end
end
```


Plot the type-2 input membership functions.

```
figure
subplot(1,2,1)
plotmf(fis2,'input',1)
title('Input 1')
subplot(1,2,2)
plotmf(fis2,'input',2)
title('Input 2')
```



The FOU adds additional uncertainty to the FIS and produces a nonlinear control surface.

```
figure
gensurf(fis2)
title('Control surface of type-2 FIS')
```

Conventional PID Controller

This example compares the fuzzy logic controller performance with that of the following conventional PID controller.

$$\text{PID}(s) = K_p + \frac{K_i}{s} + \frac{K_d s}{\tau_f s + 1}$$

Here, K_p is proportional gain, K_i is integrator gain, K_d is derivative gain, and τ_f is the derivative filter time constant.

Configure Simulation

Define the nominal plant model.

```
C = 0.5;
L = 0.5;
T = 0.5;
G = tf(C,[T 1], 'Outputdelay',L);
```

Generate the conventional PID controller parameters using pidtune.

```
pidController = pidtune(G, 'pidf');
```

In this example, the reference (r) is a step signal and $t_r = 0$, which results in $C_e = 1$ as follows.

$$C_e = \frac{1}{r(t_r) - y(t_r)} = \frac{1}{1 - 0} = 1.$$

$C_e = 1;$

To configure the simulation, use the following nominal controller parameters.

$\tau_c = 0.2;$


$C_d = \min(T, L/2) * C_e;$

$C_0 = 1 / (C * C_e * (\tau_c + L/2));$

$C_1 = \max(T, L/2) * C_0;$

To simulate the controllers, use the comparepidcontrollers Simulink model.

```
model = 'comparepidcontrollers';
load_system(model)
```




Simulate Nominal Process

Simulate the model at the nominal operating conditions.

```
out1 = sim(model);
```

Plot the step response of the system for all three controllers.

```
plotTitle = ['Nominal: C=' num2str(C) ', L=' num2str(L) ', T=' num2str(T)];
plotOutput(out1, plotTitle)
```



Obtain the step-response characteristics of the system for each controller. Here, rise time and settling time are in seconds, overshoot is a percentage of the final value, and the absolute error is integrated over the step response.

```
stepResponseTable(out1)
```

```
ans=3x4 table
```

	Rise Time	Overshoot	Settling Time	Absolute Error
PID	0.62412	11.234	4.5583	1.04
Type-1 FLC	1.4267	0	4.1023	1.1522
Type-2 FLC	1.8662	0	5.129	1.282

For the nominal process:

- Both the type-1 and type-2 fuzzy logic controllers outperform the conventional PID controller in terms of overshoot.
- The conventional PID controller, performs better with respect to rise-time and integral of absolute error (IAE).
- The type-1 FLC performs better than the type-2 FLC in terms of rise-time, settling-time, and IAE.

Simulate Modified Process

Modify the plant model by increasing the gain, time delay, and time constant values as compared to the nominal process.


```
C = 0.85;
L = 0.6;
T = 0.6;
G = tf(C,[T 1], 'Outputdelay',L);
```

Simulate the model using the updated plant parameters.

```
out2 = sim(model);
```

Plot the step response of the system for all three controllers.

```
plotTitle = ['Modified 1: C=' num2str(C) ',L=' num2str(L) ',T=' num2str(T)];
plotOutput(out2,plotTitle)
```



Obtain the step-response characteristics of the system for each controller.

```
stepResponseTable(out2)
```

ans=3x4 table

	Rise Time	Overshoot	Settling Time	Absolute Error
PID	0.38464	80.641	29.458	4.7486
Type-1 FLC	0.47262	24.877	4.6788	1.1137
Type-2 FLC	0.47262	22.787	3.4561	1.076

For this modified process:

- The conventional PID controller exhibits significant overshoot, larger settling-time, and higher IAE as compared to the fuzzy logic controllers
- For all performance measures, the type-2 FLC produces the same or superior performance compared to the type-1 FLC.

Conclusion

Overall, the type-1 FLC produces superior performance for the nominal plant as compared to the conventional PID controller. The type-2 FLC shows more robust performance for the modified plant.

The robustness of the conventional PID controller can be improved using different methods, such as prediction or multiple PID controller configurations. On the other hand, the performance of a type-2 FLC can be improved by using a different:

- Rule base
- Number of rules
- FOU


For example, you can create a type-2 FLC that defines the FOU using both the lower MF scaling factor and lower MF lag.

For `fis2`, set the lower MF scale and lag values to `0.7` and `0.1`, respectively for all input membership functions.

```
for i = 1:length(fis2.Inputs)
    for j = 1:length(fis2.Inputs(i).MembershipFunctions)
        fis2.Inputs(i).MembershipFunctions(j).LowerScale = 0.7;
        fis2.Inputs(i).MembershipFunctions(j).LowerLag = 0.1;
    end
end
```

Plot the updated membership functions.


```
figure
subplot(1,2,1)
plotmf(fis2,'input',1)
title('Input 1')
subplot(1,2,2)
plotmf(fis2,'input',2)
title('Input 2')
```



Simulate the model using the nominal plant, and plot the step responses for the controllers.

```
C = 0.5;
L = 0.5;
T = 0.5;
G = tf(C,[T 1], 'Outputdelay',L);
```

```
out4 = sim(model);
close_system(model,0)
plotTitle = ['Nominal: C=' num2str(C) ', L=' num2str(L) ', T=' num2str(T)];
plotOutput(out4,plotTitle)
```



Obtain the step-response characteristics of the system for each controller.

```
stepResponseTable(out4)
```

```
ans=3x4 table
```


	Rise Time	Overshoot	Settling Time	Absolute Error
PID	0.62412	11.234	4.5583	1.04
Type-1 FLC	1.4267	0	4.1023	1.1522
Type-2 FLC	1.2179	0	3.8746	1.1087

In this case, the updated FOU of type-2 FLC improves the rise-time of the step response.

However, the lower MF lag values also increase the overshoot in the case of the modified plant.

```
C = 0.85;
L = 0.6;
T = 0.6;
G = tf(C,[T 1], 'Outputdelay',L);

out5 = sim(model);
plotTitle = ['Nominal: C=' num2str(C) ', L=' num2str(L) ', T=' num2str(T)];
plotOutput(out5,plotTitle)
```



```
t = stepResponseTable(out5)
```

t=3x4 table

	Rise Time	Overshoot	Settling Time	Absolute Error
PID	0.38464	80.641	29.458	4.7486
Type-1 FLC	0.47262	24.877	4.6788	1.1137
Type-2 FLC	0.47262	26.699	4.6812	1.1278

Therefore, to obtain desired step response characteristics, you can vary the lower MF scale and lag values to find a suitable combination.

You can further improve the fuzzy logic controller outputs using a Mamdani type FIS since it also provides lower MF scale and lag parameters for output membership functions. However, a Mamdani type-2 FLC introduces additional computational delay due to the expensive type-reduction process.

References

[1] Mendel, J. M., *Uncertain Rule-Based Fuzzy Systems: Introduction and New Directions*, Second Edition, Springer, 2017, pp. 229-234, 600-608.

Local Functions

```
function plotOutput(out,plotTitle)
figure
```



```

plot([0 20],[1 1])
hold on
plot(out.yout{1}.Values)
plot(out.yout{2}.Values)
plot(out.yout{3}.Values)
hold off
grid minor
xlabel('Time (sec)')
ylabel('Output')
title(plotTitle)
legend(["Reference", "PID", "Type-1 FLC", "Type-2 FLC"], 'Location', "best")
end

function t = stepResponseTable(out)
s = stepinfo(out.yout{1}.Values.Data,out.yout{1}.Values.Time);
stepResponseInfo(1).RiseTime = s.RiseTime;
stepResponseInfo(1).Overshoot = s.Overshoot;
stepResponseInfo(1).SettlingTime = s.SettlingTime;
stepResponseInfo(1).IAE = out.yout{4}.Values.Data(end);

s = stepinfo(out.yout{2}.Values.Data,out.yout{2}.Values.Time);
stepResponseInfo(2).RiseTime = s.RiseTime;
stepResponseInfo(2).Overshoot = s.Overshoot;
stepResponseInfo(2).SettlingTime = s.SettlingTime;
stepResponseInfo(2).IAE = out.yout{5}.Values.Data(end);

s = stepinfo(out.yout{3}.Values.Data,out.yout{3}.Values.Time);
stepResponseInfo(3).RiseTime = s.RiseTime;
stepResponseInfo(3).Overshoot = s.Overshoot;
stepResponseInfo(3).SettlingTime = s.SettlingTime;
stepResponseInfo(3).IAE = out.yout{6}.Values.Data(end);

t = struct2table(stepResponseInfo,"RowNames",["PID" "Type-1 FLC" "Type-2 FLC"]);
t.Properties.VariableNames{1} = 'Rise Time';
t.Properties.VariableNames{2} = t.Properties.VariableNames{2};
t.Properties.VariableNames{3} = 'Settling Time';
t.Properties.VariableNames{4} = 'Absolute Error';
end

```

See Also

mamfistype2 | sugfistype2

More About

- “Type-2 Fuzzy Inference Systems” on page 2-7

Fuzzy Logic Image Processing

This example shows how to use fuzzy logic for image processing. Specifically, this example shows how to detect edges in an image.

An edge is a boundary between two uniform regions. You can detect an edge by comparing the intensity of neighboring pixels. However, because uniform regions are not crisply defined, small intensity differences between two neighboring pixels do not always represent an edge. Instead, the intensity difference might represent a shading effect.

The fuzzy logic approach for image processing allows you to use membership functions to define the degree to which a pixel belongs to an edge or a uniform region.

Import RGB Image and Convert to Grayscale

Import the image.


```
Irgb = imread('peppers.png');
```

`Irgb` is a 384 x 512 x 3 `uint8` array. The three channels of `Irgb` (third array dimension) represent the red, green, and blue intensities of the image.

Convert `Irgb` to grayscale so that you can work with a 2-D array instead of a 3-D array. To do so, use the `rgb2gray` function.

```
Igray = rgb2gray(Irgb);
```

```
figure  
image(Igray, 'CDataMapping', 'scaled')  
colormap('gray')  
title('Input Image in Grayscale')
```



Convert Image to Double-Precision Data

The `evalfis` function for evaluating fuzzy inference systems supports only single-precision and double-precision data. Therefore, convert `Igray` to a double array using the `im2double` function.

```
I = im2double(Igray);
```

Obtain Image Gradient


The fuzzy logic edge-detection algorithm for this example relies on the image gradient to locate breaks in uniform regions. Calculate the image gradient along the x-axis and y-axis.

`Gx` and `Gy` are simple gradient filters. To obtain a matrix containing the x-axis gradients of `I`, you convolve `I` with `Gx` using the `conv2` function. The gradient values are in the `[-1 1]` range. Similarly, to obtain the y-axis gradients of `I`, convolve `I` with `Gy`.


```
Gx = [-1 1];
Gy = Gx';
Ix = conv2(I,Gx,'same');
Iy = conv2(I,Gy,'same');
```

Plot the image gradients.

```
figure
image(Ix,'CDataMapping','scaled')
colormap('gray')
title('Ix')
```



```
figure
image(Iy, 'CDataMapping', 'scaled')
colormap('gray')
title('Iy')
```



You can use other filters to obtain the image gradients, such as the Sobel operator or the Prewitt operator. For information about how you can filter an image using convolution, see “What Is Image Filtering in the Spatial Domain?” (Image Processing Toolbox)

Alternatively, if you have the Image Processing Toolbox software, you can use the `imfilter` (Image Processing Toolbox), `imgradientxy` (Image Processing Toolbox), or `imgradient` (Image Processing Toolbox) functions to obtain the image gradients.

Define Fuzzy Inference System (FIS) for Edge Detection

Create a fuzzy inference system (FIS) for edge detection, `edgeFIS`.

```
edgeFIS = mamfis('Name', 'edgeDetection');
```

Specify the image gradients, `Ix` and `Iy`, as the inputs of `edgeFIS`.

```
edgeFIS = addInput(edgeFIS, [-1 1], 'Name', 'Ix');
edgeFIS = addInput(edgeFIS, [-1 1], 'Name', 'Iy');
```

Specify a zero-mean Gaussian membership function for each input. If the gradient value for a pixel is 0, then it belongs to the zero membership function with a degree of 1.

```
sx = 0.1;
sy = 0.1;
edgeFIS = addMF(edgeFIS, 'Ix', 'gaussmf', [sx 0], 'Name', 'zero');
edgeFIS = addMF(edgeFIS, 'Iy', 'gaussmf', [sy 0], 'Name', 'zero');
```

s_x and s_y specify the standard deviation for the zero membership function for the I_x and I_y inputs. To adjust the edge detector performance, you can change the values of s_x and s_y . Increasing the values makes the algorithm less sensitive to the edges in the image and decreases the intensity of the detected edges.

Specify the intensity of the edge-detected image as an output of `edgeFIS`.

```
edgeFIS = addOutput(edgeFIS,[0 1], 'Name', 'Iout');
```


Specify the triangular membership functions, white and black, for `Iout`.

```
wa = 0.1;  
wb = 1;  
wc = 1;  
ba = 0;  
bb = 0;  
bc = 0.7;  
edgeFIS = addMF(edgeFIS, 'Iout', 'trimf', [wa wb wc], 'Name', 'white');  
edgeFIS = addMF(edgeFIS, 'Iout', 'trimf', [ba bb bc], 'Name', 'black');
```

As you can with s_x and s_y , you can change the values of w_a , w_b , w_c , b_a , b_b , and b_c to adjust the edge detector performance. The triplets specify the start, peak, and end of the triangles of the membership functions. These parameters influence the intensity of the detected edges.

Plot the membership functions of the inputs and outputs of `edgeFIS`.

```
figure  
subplot(2,2,1)  
plotmf(edgeFIS, 'input', 1)  
title('Ix')  
subplot(2,2,2)  
plotmf(edgeFIS, 'input', 2)  
title('Iy')  
subplot(2,2,[3 4])  
plotmf(edgeFIS, 'output', 1)  
title('Iout')
```



Specify FIS Rules

Add rules to make a pixel white if it belongs to a uniform region and black otherwise. A pixel is in a uniform region when the image gradient is zero in both directions. If either direction has a nonzero gradient, then the pixel is on an edge.

```
r1 = "If Ix is zero and Iy is zero then Iout is white";
r2 = "If Ix is not zero or Iy is not zero then Iout is black";
edgeFIS = addRule(edgeFIS,[r1 r2]);
edgeFIS.Rules
```

```
ans =
  1x2 fisrule array with properties:
```

```
Description
Antecedent
Consequent
Weight
Connection
```

```
Details:
```

```
Description
```

```
1  "Ix==zero & Iy==zero => Iout=white (1)"
2  "Ix~=zero | Iy~=zero => Iout=black (1)"
```

Evaluate FIS


Evaluate the output of the edge detector for each row of pixels in *I* using corresponding rows of *Ix* and *Iy* as inputs.

```
Ieval = zeros(size(I));
for ii = 1:size(I,1)
    Ieval(ii,:) = evalfis(edgeFIS,[(Ix(ii,:));(Iy(ii,:))]);
end
```

Plot Results


Plot the original grayscale image.

```
figure
image(I, 'CDataMapping', 'scaled')
colormap('gray')
title('Original Grayscale Image')
```



Plot the detected edges.

```
figure
image(Ieval, 'CDataMapping', 'scaled')
colormap('gray')
title('Edge Detection Using Fuzzy Logic')
```

See Also

`evalfis`

More About

- “Build Fuzzy Systems at the Command Line” on page 2-31

Fuzzy Inference System Tuning

- “Tuning Fuzzy Inference Systems” on page 3-2
- “Tune Fuzzy Rules and Membership Function Parameters” on page 3-6
- “Tune Fuzzy Trees” on page 3-15
- “Customize FIS Tuning Process” on page 3-20
- “Tune Mamdani Fuzzy Inference System” on page 3-28
- “Tune FIS Tree for Gas Mileage Prediction” on page 3-38
- “Optimize FIS Parameters with k-Fold Cross-Validation” on page 3-51
- “Predict Chaotic Time Series Using Type-2 FIS” on page 3-58
- “Tune Fuzzy Robot Obstacle Avoidance System Using Custom Cost Function” on page 3-71
- “Classify Pixels Using Fuzzy Systems” on page 3-82
- “Autonomous Parking Using Fuzzy Inference System” on page 3-98
- “Design Controller for Artificial Pancreas Using Fuzzy Logic” on page 3-114
- “Explain Black-Box Model Using Fuzzy Support System” on page 3-131
- “Explainable Fuzzy Support System for Black-Box Model of Robot Obstacle Avoidance” on page 3-154
- “Neuro-Adaptive Learning and ANFIS” on page 3-171
- “Train Adaptive Neuro-Fuzzy Inference Systems” on page 3-177
- “Save Training Error Data to MATLAB Workspace” on page 3-187
- “Predict Chaotic Time-Series Using ANFIS” on page 3-193
- “Modeling Inverse Kinematics in a Robotic Arm” on page 3-201
- “Adaptive Noise Cancellation Using ANFIS” on page 3-209
- “Nonlinear System Identification” on page 3-217
- “Gas Mileage Prediction” on page 3-227


Tuning Fuzzy Inference Systems

Designing a complex fuzzy inference system (FIS) with a large number of inputs and membership functions (MFs) is a challenging problem due to the large number of MF parameters and rules. To design such a FIS, you can use a data-driven approach to learn rules and tune FIS parameters. To tune a fuzzy system, use the `tunefis` function and configure the tuning process using a `tunefisOptions` object.


Using Fuzzy Logic Toolbox software, you can tune both type-1 and type-2 FISs as well as FIS trees. For examples, see “Predict Chaotic Time Series Using Type-2 FIS” on page 3-58 and “Tune FIS Tree for Gas Mileage Prediction” on page 3-38.

During training, the optimization algorithm generates candidate FIS parameter sets. The fuzzy system is updated with each parameter set and then evaluated using the input training data.

If you have input/output training data, the cost for each solution is computed based on the difference between the output of the fuzzy system and the expected output values from the training data. For an example that uses this approach, see Tune Mamdani Fuzzy Inference System on page 3-28.



If you do not have input/output training data, you can specify a custom model and cost function for evaluating candidate FIS parameter sets. The cost measurement function sends an input to the fuzzy system and receives the evaluated output. The cost is based on the difference between the evaluated output and the output expected by the model. For more information and an example that uses this approach, see “Tune Fuzzy Robot Obstacle Avoidance System Using Custom Cost Function” on page 3-71.



For more information on tuning fuzzy systems see the following examples.

- “Tune Fuzzy Rules and Membership Function Parameters” on page 3-6
- “Tune Fuzzy Trees” on page 3-15
- “Customize FIS Tuning Process” on page 3-20

Tuning Methods

The following table shows the tuning methods supported by the `tunefis` function. These tuning methods find the optimal FIS parameters

Method	Description	More Information
Genetic algorithm	Population-based global optimization method that searches randomly by mutation and crossover among population members	“What Is the Genetic Algorithm?” (Global Optimization Toolbox)
Particle swarm optimization	Population-based global optimization method in which population members step throughout a search region	“What Is Particle Swarm Optimization?” (Global Optimization Toolbox)

Method	Description	More Information
Pattern search	Direct-search local optimization method that searches a set of points near the current point to find a new optimum	“What Is Direct Search?” (Global Optimization Toolbox)
Simulated annealing	A local optimization method that simulates a heating and cooling process to that finds a new optimal point near the current point	“What Is Simulated Annealing?” (Global Optimization Toolbox)
Adaptive neuro-fuzzy inference	Back-propagation algorithm that tunes membership function parameters. Alternatively, you can use the <code>anfis</code> function.	“Neuro-Adaptive Learning and ANFIS” on page 3-171

The first four tuning methods require Global Optimization Toolbox software.

Global optimization methods, such as genetic algorithms and particle swarm optimization, perform better for large parameter tuning ranges. These algorithms are useful for both the rule-learning and parameter-tuning stages of FIS optimization.

On the other hand, local search methods, such as pattern search and simulated annealing, perform better for small parameter ranges. If a FIS is generated from training data using `genfis` or a rule base is already added to a FIS using training data, then these algorithms can produce faster convergence compared to global optimization methods.

Prevent Overfitting of Tuned System

Data overfitting is a common problem in FIS parameter optimization. When overfitting occurs, the tuned FIS produces optimized results for the training data set but performs poorly for a test data set. To overcome the data overfitting problem, a tuning process can stop early based on an unbiased evaluation of the model using a separate validation dataset.

When tuning using the `tunefis` function, you can prevent overfitting using k-fold cross validation. To prevent For more information and an example, see “Optimize FIS Parameters with k-Fold Cross-Validation” on page 3-51.

Improve Tuning Results

To improve the performance of your tuned fuzzy systems, consider the following guidelines.

- Use multiple phases in your tuning process. For example, first learn the rules of a fuzzy system, and then tune input/output MF parameters using the learned rule base.
- Increase the number of iterations in both the rule-learning and parameter-tuning phases. Doing so increases the duration of the optimization process and can also increase validation error due to overtuned system parameters with the training data. To avoid overfitting, train your system using k-fold cross validation.

- Change the clustering technique used by `genfis`. Depending on the clustering technique, the generated rules can differ in their representation of the training data. Hence, the use of different clustering techniques can affect the performance of `tunefis`.
- Change FIS properties. Try changing properties such as the type of FIS, number of inputs, number of input/output MFs, MF types, and number of rules. A Sugeno system has fewer output MF parameters (assuming constant MFs) and faster defuzzification. Therefore, for fuzzy systems with a large number of inputs, a Sugeno FIS generally converges faster than a Mamdani FIS. Small numbers of MFs and rules reduce the number of parameters to tune, producing a faster tuning process. Furthermore, a large number of rules might overfit the training data.
- Modify tunable parameter settings for MFs and rules. For example, you can tune the support of a triangular MF without changing its peak location. Doing so reduces the number of tunable parameters and can produce a faster tuning process for specific applications. For rules, you can exclude zero MF indices by setting the `AllLowEmpty` tunable setting to false, which reduces the overall number of rules during the learning phase.

To improve the tuning results for fuzzy trees, consider the following guidelines.

- You can separately tune the parameters of each FIS in a FIS tree. You can then tune all the fuzzy systems together to generalize the parameter values.
- Change FIS tree properties, such as the number of fuzzy systems and the connections between the fuzzy systems.
- Use different rankings and groupings of the inputs to a FIS tree. For more information about creating FIS trees, see *Fuzzy Trees* on page 2-52.

See Also

`tunefis` | `getTunableSettings` | `genfis`

More About

- “Tune Mamdani Fuzzy Inference System” on page 3-28
- “Tune FIS Tree for Gas Mileage Prediction” on page 3-38
- “Predict Chaotic Time Series Using Type-2 FIS” on page 3-58

Tune Fuzzy Rules and Membership Function Parameters

This example shows how to tune a fuzzy inference system (FIS). Using the `tunefis` function, you can:

- Tune membership function parameters for input and output variables.
- Learn fuzzy rules.
- Tune the antecedent and consequent parameters of fuzzy rules.

For more information on tuning a FIS, see “Tuning Fuzzy Inference Systems” on page 3-2.

Tune Membership Function Parameters

For both type-1 and type-2 FISs, you can specify tunable parameter settings for the input and output MFs and tune the values of the selected parameters. You can tune the parameters for any combination of input and output MFs. This example shows an example workflow using a type-1 FIS. For an example that tunes a type-2 FIS, see “Predict Chaotic Time Series Using Type-2 FIS” on page 3-58.

Create a FIS.

```

fis = mamfis;
fis = addInput(fis,[0 10], 'NumMFs',3);
fis = addOutput(fis,[0 1], 'NumMFs',3);
fis = addRule(fis,[1 1 1 1;1 1 1 1;1 1 1 1]);

```

Extract input and output parameter settings from the FIS.

```
[in,out] = getTunableSettings(fis)
```

```

in = VariableSettings with properties:
    Type: "input"
    VariableName: "input1"
    MembershipFunctions: [1x3 fuzzy.tuning.MembershipFunctionSettings]
    FISName: "fis"

```

```

out = VariableSettings with properties:
    Type: "output"
    VariableName: "output1"
    MembershipFunctions: [1x3 fuzzy.tuning.MembershipFunctionSettings]
    FISName: "fis"

```

The parameter settings are represented by `VariableSettings` objects that include the FIS name, variable type, variable name, and MF parameter settings. Examine the parameter settings of MF 1 of input 1.

```
in(1).MembershipFunctions(1).Parameters
```

```

ans = NumericParameters with properties:
    Minimum: [-Inf -Inf -Inf]
    Maximum: [Inf Inf Inf]
    Free: [1 1 1]

```


For each parameter value of an input or output MF, you can specify its availability for tuning and its minimum and maximum values. By default, all MF parameters are free for tuning and their ranges are set to [- Inf, Inf].

You can specify the tunability of all parameters in an MF using the `setTunable` function. For example, make MF 1 of input 1 nontunable.

```
in(1).MembershipFunctions(1) = setTunable(in(1).MembershipFunctions(1),false);
```

You can also specify the tunability of individual MF parameters. Make the first parameter of MF 2 of input 1 nontunable.

```
in(1).MembershipFunctions(2).Parameters.Free(1) = false;
```

For each parameter, you can specify the range of possible values. For example, set the minimum values for the second and third parameters of MF 3 of input 1 to 0.

```
in(1).MembershipFunctions(3).Parameters.Minimum(2:3) = 0;
```

Similarly, set the maximum values for second and third parameters of MF 3 of input 1 to 15.

```
in(1).MembershipFunctions(3).Parameters.Maximum(2:3) = 15;
```

The tuning process sets the default minimum and maximum range values of tunable MF parameters to their corresponding input or output ranges.

Finally, make the MF parameters of all output membership functions nontunable.

```
out = setTunable(out,false);
```

Specify input and output training data. For this example, generate training data using the following function.

$$y = \left| \frac{\sin(2x)}{e^{x/5}} \right|$$

```
x = (0:0.1:10)';
y = abs(sin(2*x)./exp(x/5));
```

Specify options for `tunefis`. For this example, use the genetic algorithm tuning method. Use a maximum of five generations for optimization.

```
options = tunefisOptions("Method","ga");
options.MethodOptions.MaxGenerations = 5;
```

If you have Parallel Computing Toolbox™ software, you can improve the speed of the tuning process by setting `options.UseParallel` to `true`. If you do not have Parallel Computing Toolbox software, set `options.UseParallel` to `false`, which is the default value.

By default, `tunefis` uses the root mean squared error (RMSE) for cost calculation. You can change the cost function to `norm1` or `norm2` by setting `options.DistanceMetric`.

```
options.DistanceMetric = "norm1";
```

Tune `fis` using the parameter settings, training data, and tuning options.

```
rng('default') % for reproducibility
[fisout,optimout] = tunefis(fis,[in;out],x,y,options);
```

Generation	Func-count	Best f(x)	Mean f(x)	Stall Generations
1	100	32.84	32.84	0
2	147	32.84	32.84	1
3	194	32.84	32.84	2
4	241	32.84	32.84	3
5	288	32.84	32.84	4

Optimization terminated: maximum number of generations exceeded.

`fisout` includes the updated parameter values. `optimout` provides additional outputs of the optimization method and any error messages that are returned during the update process of the input fuzzy system using the optimized parameter values.

`optimout`

```
optimout = struct with fields:
  tuningOutputs: [1x1 struct]
  totalFcnCount: 288
  totalRuntime: 2.7104
  errorMessage: []
```

`optimout.tuningOutputs`

```
ans = struct with fields:
  x: [5 9.1667 5.8333 10 14.1667]
  fval: 32.8363
  exitflag: 0
  output: [1x1 struct]
  population: [50x5 double]
  scores: [50x1 double]
```

You can optionally tune `fis` using either the input or output parameter settings only. In this example, since you set the output parameter settings to nontunable, tuning the FIS with just the input parameter settings produces the same results.

```
rng('default')
[fisout,optimout] = tunefis(fis,in,x,y,options);
```

Generation	Func-count	Best f(x)	Mean f(x)	Stall Generations
1	100	32.84	32.84	0
2	147	32.84	32.84	1
3	194	32.84	32.84	2
4	241	32.84	32.84	3
5	288	32.84	32.84	4

Optimization terminated: maximum number of generations exceeded.

`optimout`

```
optimout = struct with fields:
  tuningOutputs: [1x1 struct]
  totalFcnCount: 288
  totalRuntime: 1.4074
  errorMessage: []
```

`optimout.tuningOutputs`

```
ans = struct with fields:
    x: [5 9.1667 5.8333 10 14.1667]
    fval: 32.8363
    exitflag: 0
    output: [1x1 struct]
    population: [50x5 double]
    scores: [50x1 double]
```

Tune Fuzzy Rules

In addition to tuning membership function parameters, you can tune the antecedent and consequent parameters of the rules in a fuzzy system.

Obtain rule parameter settings from a fuzzy system using `getTunableSettings`.

```
[~,~,rule] = getTunableSettings(fis)

rule=3x1 RuleSettings array with properties:
    Index
    Antecedent
    Consequent
    FISName
```

Each rule parameter setting includes the FIS name, the index of the rule in the FIS, and parameter settings for the rule antecedent and consequent (the *rule clauses*).

For a rule clause, you can set the following parameters settings.

- **AllowNot** — Allow the use of NOT logic, that is, negative MF indices. By default, rules do not allow NOT logic.
- **Free** — Make the input/output MF indices available for tuning. By default, clause parameters are available for tuning.
- **AllowEmpty** — Allow the absence of input/output variables, that is, zero MF indices. By default, the absence of a variable is allowed.

```
rule(1).Antecedent(1)

ans = ClauseParameters with properties:
    AllowNot: 0
    AllowEmpty: 1
    Free: 1
```

Allow NOT logic in the antecedent of rule 1.

```
rule(1).Antecedent.AllowNot = true;
```

Make the consequent of rule 1 not available for tuning.

```
rule(1).Consequent.Free = 0;
```

Do not allow absence of a variable in the consequent of rule 2.

```
rule(2).Consequent.AllowEmpty = false;
```

Set rule 3 as nontunable.

```
rule(3) = setTunable(rule(3),false);
```

Set `options.DistanceMetric` to `norm2`.

```
options.DistanceMetric = "norm2";
```

Tune `fis` using the rule parameter settings.

```
rng('default') % for reproducibility
fisout = tunefis(fis,rule,x,y,options);
```

Generation	Func-count	Best f(x)	Mean f(x)	Stall Generations
1	100	1.648	2.575	0
2	147	1.648	2.448	1
3	194	1.648	2.212	2
4	241	1.648	2.052	3
5	288	1.648	1.874	4

Optimization terminated: maximum number of generations exceeded.

Since you specified rule 3 as nontunable, you can exclude rule 3 when you tune `fis`. Doing so produces the same tuning result.

```
rng('default') % for reproducibility
fisout = tunefis(fis,rule(1:2),x,y,options);
```

Generation	Func-count	Best f(x)	Mean f(x)	Stall Generations
1	100	1.648	2.575	0
2	147	1.648	2.448	1
3	194	1.648	2.212	2
4	241	1.648	2.052	3
5	288	1.648	1.874	4

Optimization terminated: maximum number of generations exceeded.

Learn Fuzzy Rules

You can configure `tunefis` to learn the rules of a fuzzy system. To do so, set the `OptimizationType` option of `tunefisOptions` to `"learning"`.

```
fisin = fis;
fisin.Rules = [];
options.OptimizationType = "learning";
```

Set the maximum number of rules in the tuned FIS to 3.

```
options.NumMaxRules = 3;
```

The size of the tuned rule base might be less than `NumMaxRules`, because `tunefis` removes duplicate rules from the tuned FIS. If you do not specify `NumMaxRules`, then `tunefis` adds the maximum number of rules determined by the possible combinations of input MFs. The default input MF combinations include zero MF indices, which allow absence of variables. The default combinations exclude negative MF indices, so that NOT logic is not allowed.

Set `options.DistanceMetric` to `"rmse"` and tune the FIS.

```
options.DistanceMetric = "rmse";
rng('default') % for reproducibility
fisout = tunefis(fisin,[],x,y,options);
```

Generation	Func-count	Best f(x)	Mean f(x)	Stall Generations
1	400	0.165	0.2956	0
2	590	0.165	0.2805	1
3	780	0.165	0.2578	2
4	970	0.165	0.2393	3
5	1160	0.165	0.2322	4

Optimization terminated: maximum number of generations exceeded.

During the tuning process, the FIS automatically learns rules after cost optimization with the training data. Examine the tuned rules.

`fisout.Rules`

```
ans = 1x3 fisrule array with properties:
    Description
    Antecedent
    Consequent
    Weight
    Connection
```

Details:

	Description
1	"input1==mf3 => output1=mf1 (1)"
2	"input1==mf1 => output1=mf2 (1)"
3	"input1==mf2 => output1=mf1 (1)"

You can remove some of the existing rules and learn additional rules.

```
fisout.Rules(2:end) = [];
rng('default') % for reproducibility
fisout = tunefis(fisin,[],x,y,options);
```

Generation	Func-count	Best f(x)	Mean f(x)	Stall Generations
1	400	0.165	0.2956	0
2	590	0.165	0.2805	1
3	780	0.165	0.2578	2
4	970	0.165	0.2393	3
5	1160	0.165	0.2322	4

Optimization terminated: maximum number of generations exceeded.

`fisout.Rules`

```
ans = 1x3 fisrule array with properties:
    Description
    Antecedent
    Consequent
    Weight
    Connection
```

Details:

	Description
1	"input1==mf3 => output1=mf1 (1)"

```
2 "input1==mf1 => output1=mf2 (1)"
3 "input1==mf2 => output1=mf1 (1)"
```

You can also tune the antecedents and consequents of existing rules and learn new rules. To do so, obtain the tunable rule parameter settings and pass them to the `tunefis` function.

```
fisout.Rules(2:end) = [];
fisout.Rules(1).Antecedent = 1;
fisout.Rules(1).Consequent = 1;
[~,~,rule] = getTunableSettings(fisout);
rng('default')
fisout = tunefis(fisin,rule,x,y,options);
```

Generation	Func-count	Best f(x)	Mean f(x)	Stall Generations
1	400	0.165	0.3063	0
2	590	0.165	0.2845	1
3	780	0.165	0.2549	2
4	970	0.165	0.2344	3
5	1160	0.165	0.2153	4

Optimization terminated: maximum number of generations exceeded.

`fisout.Rules`

`ans = 1x3 fisrule array with properties:`

```
Description
Antecedent
Consequent
Weight
Connection
```

Details:

	Description
1	"input1==mf1 => output1=mf2 (1)"
2	"input1==mf2 => output1=mf1 (1)"
3	"input1==mf3 => output1=mf1 (1)"

Tune MF and Rule Parameters

You can tune all MF and rule parameters simultaneously. First, obtain all parameter settings for the FIS.

```
[in,out,rule] = getTunableSettings(fis);
```

Configure the tuning options.

```
options = tunefisOptions('Method','ga');
options.MethodOptions.MaxGenerations = 5;
```

Tune the MF and rule parameters of the FIS.

```
rng('default') % for reproducibility
fisout = tunefis(fis,[in;out;rule],x,y,options);
```

Generation	Func-count	Best f(x)	Mean f(x)	Stall Generations
------------	------------	--------------	--------------	----------------------

1	400	0.165	0.296	0
2	590	0.1638	0.2821	0
3	780	0.1625	0.2697	0
4	970	0.1625	0.2605	1
5	1160	0.1604	0.2546	0

Optimization terminated: maximum number of generations exceeded.

For a large fuzzy system, if you tune all FIS parameters in the same tuning process, obtaining the expected results can take several iterations. To improve the tuning time, you can tune parameters using the following two steps.

- 1 Tune or learn rule parameters only.
- 2 Tune both MF and rule parameters.

Learning and tuning rules is less computationally expensive than tuning the MF parameters, due to the small number of rule parameters. Therefore, the first step quickly converges to a fuzzy rule base during training. In the second step, using the rule base from the first step as an initial condition improves convergence of the parameter tuning process.

Generate FIS from Data and Tune

When you manually create a FIS for tuning, you must either manually create an initial rule base or learn the initial rules. Alternatively, you can generate a FIS using the `genfis` function, which creates an initial rule base based on your training data. You can then optimize the FIS using `tunefis`. In this approach, the tuning process can employ a local optimization method because the rule base is derived from the training data.

This example uses the same training data as the preceding examples.

Create options for `genfis` that specify five MFs, a Gaussian MF for the input, and a constant MF for the output.

```
goptions = genfisOptions('GridPartition','NumMembershipFunctions',5, ...
    'InputMembershipFunctionType','gaussmf', ...
    'OutputMembershipFunctionType','constant');
```

Generate the initial FIS and get its parameter settings.

```
fisin = genfis(x,y,goptions);
[in,out,rule] = getTunableSettings(fisin);
```

Use the pattern search method for optimization, setting the maximum number of iterations to 25, and tune the FIS.

```
toptions = tunefisOptions('Method','patternsearch');
toptions.MethodOptions.MaxIterations = 25;
rng('default')
fisout = tunefis(fisin,[in;out],x,y,toptions);
```

Iter	Func-count	f(x)	MeshSize	Method
0	1	0.346649	1	
1	19	0.346649	0.5	Refine Mesh
2	37	0.273812	1	Successful Poll
3	38	0.236413	2	Successful Poll
4	39	0.190794	4	Successful Poll
5	40	0.182142	8	Successful Poll
6	47	0.182142	4	Refine Mesh

7	49	0.162927	8	Successful Poll
8	56	0.162927	4	Refine Mesh
9	67	0.162927	2	Refine Mesh
10	69	0.159539	4	Successful Poll
11	80	0.159539	2	Refine Mesh
12	92	0.159539	1	Refine Mesh
13	94	0.159421	2	Successful Poll
14	106	0.159373	4	Successful Poll
15	117	0.159373	2	Refine Mesh
16	125	0.159185	4	Successful Poll
17	136	0.159185	2	Refine Mesh
18	151	0.159185	1	Refine Mesh
19	152	0.15914	2	Successful Poll
20	167	0.15914	1	Refine Mesh
21	170	0.158914	2	Successful Poll
22	185	0.158914	1	Refine Mesh
23	187	0.158839	2	Successful Poll
24	202	0.158839	1	Refine Mesh
25	206	0.158366	2	Successful Poll
26	215	0.158121	4	Successful Poll

Maximum number of iterations exceeded: increase options.MaxIterations.

You can increase the number of iterations to further optimize the cost.

See Also

`tunefis | getTunableSettings | genfis`

More About


- “Tune Mamdani Fuzzy Inference System” on page 3-28
- “Tune FIS Tree for Gas Mileage Prediction” on page 3-38
- “Tune Fuzzy Trees” on page 3-15

Tune Fuzzy Trees

This example shows how to tune the parameters of a FIS tree using a two-step process. For more information about a similar two-step process, see “Tuning Fuzzy Inference Systems” on page 3-2.

- Learn and tune the rules of the FISs in the tree.
- Learn the MF parameters of the FISs in the tree.

Create a FIS tree to model $\frac{\sin(x) + \cos(x)}{\exp(x)}$, as shown in the following figure. For more information on creating FIS trees, see “Fuzzy Trees” on page 2-52.



Create `fis1` as a Sugeno-type FIS, which results in a faster tuning process compared to a Mamdani system, due to its computationally efficient defuzzification method. Add two inputs, both with range [0, 10] and with three MFs each. Use a smooth, differentiable MF, such as `gaussmf`, to match the characteristics of the data type you are modeling.

```

fis1 = sugfis('Name', 'fis1');
fis1 = addInput(fis1,[0 10], 'NumMFs',3, 'MFTYPE', 'gaussmf');
fis1 = addInput(fis1,[0 10], 'NumMFs',3, 'MFTYPE', 'gaussmf');
  
```

Add an output with the range [-1.5, 1.5] having nine MFs corresponding to the nine possible input MF combinations. Doing so provides maximum granularity for the FIS rules. Set the output range according to the possible values of $\sin(x) + \cos(x)$.

```

fis1 = addOutput(fis1,[-1.5 1.5], 'NumMFs',9);
  
```

Create `fis2` as a Sugeno-type FIS. Add two inputs. Set the range of the first input to [-1.5, 1.5], which matches the range of the output of `fis1`. The second input is the same as the inputs of `fis1`. Therefore, use the same input range, [0, 10]. Add three MFs for each of the inputs.

```

fis2 = sugfis('Name', 'fis2');
fis2 = addInput(fis2,[-1.5 1.5], 'NumMFs',3, 'MFTYPE', 'gaussmf');
fis2 = addInput(fis2,[0 10], 'NumMFs',3, 'MFTYPE', 'gaussmf');
  
```

Add an output with range [0, 1] and nine MFs. The output range is set according to the possible values of $\frac{\sin(x) + \cos(x)}{\exp(x)}$.

```
fis2 = addOutput(fis2,[0 1], 'NumMFs',9);
```

Connect the inputs and the outputs as shown in the diagram. The first output of `fis1`, `output1`, connects to the first input of `fis2`, `input1`. The inputs of `fis1` connect to each other, and the second input of `fis1` connects to the second input of `fis2`.

```
con1 = ["fis1/output1" "fis2/input1"];
con2 = ["fis1/input1" "fis1/input2"];
con3 = ["fis1/input2" "fis2/input2"];
```

Finally, create a FIS tree using the specified FISs and connections.

```
fisT = fistree([fis1 fis2],[con1;con2;con3]);
```

Add an additional output to the FIS tree to access the output of `fis1`.

```
fisT.Outputs = ["fis1/output1";fisT.Outputs];
```

Generate input and output training data.

```
x = (0:0.1:10)';
y1 = sin(x)+cos(x);
y2 = y1./exp(x);
y = [y1 y2];
```

Tune the FIS tree parameters in two steps. First, learn the rules of the FIS tree using a global optimization method. For this example, use particle swarm.

```
options = tunefisOptions('Method','particleswarm','OptimizationType','learning');
```

This tuning step uses a small number of iterations to learn a rule base without overfitting the training data. The rule base provides an educated initial condition that the second step can use to optimize all the FIS tree parameters together. Set the maximum iteration number to 5, and learn the rule base.

```
options.MethodOptions.MaxIterations = 5;
rng('default') % for reproducibility
fisTout1 = tunefis(fisT,[],x,y,options);
```

Iteration	f-count	Best f(x)	Mean f(x)	Stall Iterations
0	100	0.6682	0.9395	0
1	200	0.6682	1.023	0
2	300	0.6652	0.9308	0
3	400	0.6259	0.958	0
4	500	0.6259	0.918	1
5	600	0.5969	0.9179	0

Optimization ended: number of iterations exceeded OPTIONS.MaxIterations.

Next, to tune all the FIS tree parameters at once, use a local optimization method. For this example, use pattern search. Local optimization is generally faster than global optimization and can produce better results when the input fuzzy system parameters are already consistent with the training data.

Use the `patternsearch` method for optimization. Set the number of iterations to 25.

```
options.Method = 'patternsearch';
options.MethodOptions.MaxIterations = 25;
```

Use `getTunableSettings` to obtain input, output, and rule parameter settings from the FIS tree.

```
[in,out,rule] = getTunableSettings(fisTout1);
```

Tune the FIS tree parameters.

```
rng('default') % for reproducibility
fisTout2 = tunefis(fisTout1,[in;out;rule],x,y,options);
```

Iter	Func-count	f(x)	MeshSize	Method
0	1	0.596926	1	
1	3	0.551284	2	Successful Poll
2	13	0.548551	4	Successful Poll
3	20	0.546331	8	Successful Poll
4	33	0.527482	16	Successful Poll
5	33	0.527482	8	Refine Mesh
6	61	0.511532	16	Successful Poll
7	61	0.511532	8	Refine Mesh
8	92	0.505355	16	Successful Poll
9	92	0.505355	8	Refine Mesh
10	128	0.505355	4	Refine Mesh
11	175	0.487734	8	Successful Poll
12	212	0.487734	4	Refine Mesh
13	265	0.487734	2	Refine Mesh
14	275	0.486926	4	Successful Poll
15	328	0.486926	2	Refine Mesh
16	339	0.483683	4	Successful Poll
17	391	0.483683	2	Refine Mesh
18	410	0.442624	4	Successful Poll
19	462	0.442624	2	Refine Mesh
20	469	0.44051	4	Successful Poll
21	521	0.44051	2	Refine Mesh
22	542	0.435381	4	Successful Poll
23	594	0.435381	2	Refine Mesh
24	614	0.398872	4	Successful Poll
25	662	0.398385	8	Successful Poll
26	698	0.398385	4	Refine Mesh

Maximum number of iterations exceeded: increase options.MaxIterations.

The optimization cost reduces from 0.60 to 0.40 in the second step.

Alternatively, you can tune the specific fuzzy systems separately within a FIS tree. For this example, after learning the rule base of the FIS tree, separately tune the `fis1` and `fis2` parameters.

To obtain parameter settings of a FIS within the FIS tree, use `getTunableSettings`, specifying the FIS name. First, get the parameter settings for `fis1`.

```
[in,out,rule] = getTunableSettings(fisTout1,"FIS","fis1");
```

Tune the parameters of `fis1`.

```
rng('default')
fisTout2 = tunefis(fisTout1,[in;out;rule],x,y,options);
```

Iter	Func-count	f(x)	MeshSize	Method
0	1	0.596926	1	
1	3	0.551284	2	Successful Poll
2	18	0.510362	4	Successful Poll
3	28	0.494804	8	Successful Poll
4	56	0.494804	4	Refine Mesh

5	84	0.493422	8	Successful Poll
6	107	0.492883	16	Successful Poll
7	107	0.492883	8	Refine Mesh
8	136	0.492883	4	Refine Mesh
9	171	0.492883	2	Refine Mesh
10	178	0.491534	4	Successful Poll
11	213	0.491534	2	Refine Mesh
12	229	0.482682	4	Successful Poll
13	264	0.482682	2	Refine Mesh
14	279	0.446645	4	Successful Poll
15	313	0.446645	2	Refine Mesh
16	330	0.44657	4	Successful Poll
17	364	0.44657	2	Refine Mesh
18	384	0.446495	4	Successful Poll
19	418	0.446495	2	Refine Mesh
20	461	0.445938	4	Successful Poll
21	495	0.445938	2	Refine Mesh
22	560	0.422421	4	Successful Poll
23	594	0.422421	2	Refine Mesh
24	597	0.397265	4	Successful Poll
25	630	0.397265	2	Refine Mesh
26	701	0.390338	4	Successful Poll

Maximum number of iterations exceeded: increase options.MaxIterations.

In this case, the optimization cost is improved by tuning only the `fis1` parameter values.

Next, obtain the parameter settings for `fis2` and tune the `fis2` parameters.

```
[in,out,rule] = getTunableSettings(fisTout2,"FIS","fis2");
rng('default')
fisTout3 = tunefis(fisTout2,[in;out;rule],x,y,options);
```

Iter	Func-count	f(x)	MeshSize	Method
0	1	0.390338	1	
1	2	0.374103	2	Successful Poll
2	5	0.373855	4	Successful Poll
3	10	0.356619	8	Successful Poll
4	33	0.356619	4	Refine Mesh
5	43	0.350715	8	Successful Poll
6	65	0.349417	16	Successful Poll
7	65	0.349417	8	Refine Mesh
8	87	0.349417	4	Refine Mesh
9	91	0.349356	8	Successful Poll
10	112	0.349356	4	Refine Mesh
11	138	0.346102	8	Successful Poll
12	159	0.346102	4	Refine Mesh
13	172	0.345938	8	Successful Poll
14	193	0.345938	4	Refine Mesh
15	222	0.342721	8	Successful Poll
16	244	0.342721	4	Refine Mesh
17	275	0.342721	2	Refine Mesh
18	283	0.340727	4	Successful Poll
19	312	0.340554	8	Successful Poll
20	335	0.340554	4	Refine Mesh
21	366	0.340554	2	Refine Mesh
22	427	0.337873	4	Successful Poll
23	457	0.337873	2	Refine Mesh
24	521	0.33706	4	Successful Poll

```

25         551         0.33706         2         Refine Mesh
26         624         0.333193        4         Successful Poll
Maximum number of iterations exceeded: increase options.MaxIterations.

```

The optimization cost is further reduced by tuning the `fis2` parameter values. To avoid overfitting of individual FIS parameter values, you can further tune both the `fis1` and `fis2` parameters together.

```

[in,out,rule] = getTunableSettings(fisTout3);
rng('default')
fisTout4 = tunefis(fisTout3,[in;out;rule],x,y,options);

```

Iter	Func-count	f(x)	MeshSize	Method
0	1	0.333193	1	
1	8	0.326804	2	Successful Poll
2	91	0.326432	4	Successful Poll
3	116	0.326261	8	Successful Poll
4	154	0.326261	4	Refine Mesh
5	205	0.326261	2	Refine Mesh
6	302	0.326092	4	Successful Poll
7	352	0.326092	2	Refine Mesh
8	391	0.325964	4	Successful Poll
9	441	0.325964	2	Refine Mesh
10	478	0.32578	4	Successful Poll
11	528	0.32578	2	Refine Mesh
12	562	0.325691	4	Successful Poll
13	612	0.325691	2	Refine Mesh
14	713	0.229273	4	Successful Poll
15	763	0.229273	2	Refine Mesh
16	867	0.22891	4	Successful Poll
17	917	0.22891	2	Refine Mesh
18	1036	0.228688	4	Successful Poll
19	1086	0.228688	2	Refine Mesh
20	1212	0.228688	1	Refine Mesh
21	1266	0.228445	2	Successful Poll
22	1369	0.228441	4	Successful Poll
23	1381	0.227645	8	Successful Poll
24	1407	0.226125	16	Successful Poll
25	1407	0.226125	8	Refine Mesh
26	1447	0.226125	4	Refine Mesh

Maximum number of iterations exceeded: increase options.MaxIterations.

Overall, the optimization cost is smaller after using three tuning steps than after using only one.

See Also

`tunefis` | `getTunableSettings`

More About

- “Fuzzy Trees” on page 2-52
- “Tune Mamdani Fuzzy Inference System” on page 3-28

Customize FIS Tuning Process

This example shows how to customize the FIS tuning process by specifying either a custom cost function or a custom optimization method.


For more information on tuning a FIS, see “Tune Fuzzy Rules and Membership Function Parameters” on page 3-6 and “Tune Fuzzy Trees” on page 3-15.

Tune FIS Using Custom Cost Function


You can specify a custom cost function for tuning your fuzzy system. Doing so is useful for:

- Training a FIS using a custom model without using input/output training data. For an example, see “Tune Fuzzy Robot Obstacle Avoidance System Using Custom Cost Function” on page 3-71.
- Combining the outputs of the component FISs of a FIS tree using mathematical operations, as shown in this example.

As an example, consider the FIS tree from “Tune Fuzzy Trees” on page 3-15.



Suppose you want to modify the FIS tree as shown in the following diagram, combining the FIS outputs using known mathematical operations from the training data.



Create the FIS tree, which contains three FIS objects. The outputs of the FIS tree are the outputs of the individual FIS objects.

```

fis1 = sugfis('Name','fis1');
fis1 = addInput(fis1,[0 10],'NumMFs',3,'MFTYPE','gaussmf');
fis1 = addOutput(fis1,[-1 1],'NumMFs',3);

fis2 = sugfis('Name','fis2');
fis2 = addInput(fis2,[0 10],'NumMFs',3,'MFTYPE','gaussmf');
fis2 = addOutput(fis2,[-1 1],'NumMFs',3);

fis3 = sugfis('Name','fis3');
fis3 = addInput(fis3,[0 10],'NumMFs',3,'MFTYPE','gaussmf');
fis3 = addOutput(fis3,[0 1],'NumMFs',3);

con = ["fis1/input1" "fis2/input1";"fis2/input1" "fis3/input1"];

fisT = fistree([fis1 fis2 fis3],con);

```

Generate training data.

```

x = (0:0.1:10)';
y1 = sin(x)+cos(x);
y2 = y1./exp(x);
y = [y1;y2];

```

To implement the addition and multiplication operations, use a cost function. For this example, use the custom function `customcostfcn`, included at the end of the example. Learn a rule base using this cost function.

```

options = tunefisOptions('Method',"particleswarm",'OptimizationType',"learning");
options.MethodOptions.MaxIterations = 5;
rng('default')
fisTout1 = tunefis(fisT,[],@(fis)customcostfcn(fis,x,y),options);

```

Iteration	f-count	Best f(x)	Mean f(x)	Stall Iterations
0	100	0.746	1.31	0
1	200	0.5089	1.249	0
2	300	0.5089	1.086	1
3	400	0.5089	1.112	2
4	500	0.5089	1.106	3
5	600	0.4999	1.051	0

Optimization ended: number of iterations exceeded OPTIONS.MaxIterations.

Next, tune all the parameters of the FIS tree.

```

options.Method = 'patternsearch';
options.MethodOptions.MaxIterations = 25;
[in,out,rule] = getTunableSettings(fisTout1);
rng('default')
fisTout2 = tunefis(fisTout1,[in;out;rule],@(fis)customcostfcn(fis,x,y),options);

```

Iter	Func-count	f(x)	MeshSize	Method
0	1	0.499882	1	
1	13	0.499864	2	Successful Poll
2	51	0.499727	4	Successful Poll
3	72	0.499727	2	Refine Mesh

```

4      117      0.499727      1      Refine Mesh
5      157      0.499542      2      Successful Poll
6      170      0.499485      4      Successful Poll
7      191      0.499485      2      Refine Mesh
8      217      0.499483      4      Successful Poll
9      238      0.499483      2      Refine Mesh
10     275      0.499483      4      Successful Poll
11     296      0.499483      2      Refine Mesh
12     340      0.499483      1      Refine Mesh
13     381      0.499483      2      Successful Poll
14     425      0.499483      1      Refine Mesh
15     497      0.499483      0.5    Refine Mesh
16     536      0.499394      1      Successful Poll
17     547      0.499217      2      Successful Poll
18     591      0.499217      1      Refine Mesh
19     603      0.499211      2      Successful Poll
20     630      0.498972      4      Successful Poll
21     652      0.498972      2      Refine Mesh
22     696      0.498972      1      Refine Mesh
23     768      0.498972      0.5    Refine Mesh
24     843      0.498972      0.25   Refine Mesh
25     859      0.495584      0.5    Successful Poll
26     869      0.494138      1      Successful Poll

```

Maximum number of iterations exceeded: increase options.MaxIterations.

You can add more input/output MFs and specify additional FIS tree outputs to improve the tuning performance. Using additional MF parameters and more training data for additional FIS tree outputs can further fine-tune the outputs of `fis1`, `fis2`, and `fis3`.

Tune FIS Using Custom Optimization Method

You can also implement your own FIS parameter optimization method using `getTunableSettings`, `getTunableValues`, and `setTunableValues`. This example uses these functions to tune a rule base of a fuzzy system.

Create a FIS to approximate $\sin(\theta)$, where θ varies from 0 to 2π .

```

fisin = mamfis;

```

Add an input with a range of $[0, 2\pi]$ and having five Gaussian MFs. Also, add an output with a range of $[-1, 1]$ and having five Gaussian MFs.

```

fisin = addInput(fisin,[0 2*pi], 'NumMFs',5,'MFType','gaussmf');
fisin = addOutput(fisin,[-1 1], 'NumMFs',5,'MFType','gaussmf');

```

Add five rules.

```

fisin = addRule(fisin,[1 1 1 1;2 2 1 1;3 3 1 1;4 4 1 1;5 5 1 1]);
fisin.Rules

```

```

ans =
    1x5 fisrule array with properties:

```

```

    Description
    Antecedent
    Consequent
    Weight
    Connection

```


Details:

	Description
1	"input1==mf1 => output1=mf1 (1)"
2	"input1==mf2 => output1=mf2 (1)"
3	"input1==mf3 => output1=mf3 (1)"
4	"input1==mf4 => output1=mf4 (1)"
5	"input1==mf5 => output1=mf5 (1)"

For a faster FIS update, set `DisableStructuralChecks` to `true`.

```
fisin.DisableStructuralChecks = true;
```

Obtain the rule parameter settings.

```
[~,~,rule] = getTunableSettings(fisin);
```

Make the rule antecedents nontunable. In the rule consequents, do not allow NOT logic (negative MF indices) or empty variables (zero MF indices).

```
for i = 1:numel(rule)
    rule(i).Antecedent.Free = false;
    rule(i).Consequent.AllowNot = false;
    rule(i).Consequent.AllowEmpty = false;
end
```

Generate data for tuning.

```
x = (0:0.1:2*pi)';
y = sin(x);
```

To tune the rule parameters, use the custom function `customtunefis` included at the end of this example. Set the number of iterations to 2, and do not allow invalid parameter values when updating the FIS using `setTunableValues`.

```
numite = 2;
ignoreinvp = false;
fisout = customtunefis(fisin,rule,x,y,numite,ignoreinvp);
```

```
Initial cost = 1.170519
Iteration 1: Cost = 0.241121
Iteration 2: Cost = 0.241121
```

Display the tuned rules.

```
fisout.Rules
```

```
ans =
    1x5 fisrule array with properties:
```

```
    Description
    Antecedent
    Consequent
    Weight
    Connection
```

Details:

	Description
1	"input1==mf1 => output1=mf4 (1)"
2	"input1==mf2 => output1=mf5 (1)"
3	"input1==mf3 => output1=mf3 (1)"
4	"input1==mf4 => output1=mf1 (1)"
5	"input1==mf5 => output1=mf2 (1)"

Allow NOT logic in the rules and optimize the FIS again.

```
for i = 1:numel(rule)
    rule(i).Consequent.AllowNot = true;
end
fisout = customtunefis(fisin,rule,x,y,numite,ignoreinvp);
```

```
Initial cost = 1.170519
Iteration 1: Cost = 0.357052
Iteration 2: Cost = 0.241121
```

fisout.Rules

```
ans =
    1x5 fisrule array with properties:
```

```
    Description
    Antecedent
    Consequent
    Weight
    Connection
```

Details:

	Description
1	"input1==mf1 => output1=mf4 (1)"
2	"input1==mf2 => output1=mf5 (1)"
3	"input1==mf3 => output1=mf3 (1)"
4	"input1==mf4 => output1=mf1 (1)"
5	"input1==mf5 => output1=mf2 (1)"

Using NOT logic creates more combinations of rule parameters, resulting in more iterations to tune a FIS.

Next, reset `AllowNot` to `false` and set `AllowEmpty` to `true`. In other words, allow the absence of variables (zero output MF indices) in the consequents. Tune the FIS with the updated rule parameter settings.

```
for i = 1:numel(rule)
    rule(i).Consequent.AllowNot = false;
    rule(i).Consequent.AllowEmpty = true;
end
try
    fisout = customtunefis(fisin,rule,x,y,numite,ignoreinvp);
```

```
catch me
    disp("Error: "+me.message)
end
```

```
Initial cost = 1.170519
```

```
Error: Rule consequent must have at least one nonzero membership function index.
```

The tuning process fails since the FIS contains only one output, which must be nonzero (nonempty) in the rule consequent. To ignore invalid parameter values, specify `IgnoreInvalidParameters` with `setTunableValues`.

Set `ignoreinvp` to `true`, which specifies the `IgnoreInvalidParameters` value in the call to `setTunableValues` used in `customtunefis`.

```
ignoreinvp = true;
fisout = customtunefis(fisin,rule,x,y,numite,ignoreinvp);
```

```
Initial cost = 1.170519
```

```
Iteration 1: Cost = 0.241121
```

```
Iteration 2: Cost = 0.241121
```

```
fisout.Rules
```

```
ans =
    1x5 fisrule array with properties:
```

```
    Description
    Antecedent
    Consequent
    Weight
    Connection
```

```
Details:
```

	Description
1	"input1==mf1 => output1=mf4 (1)"
2	"input1==mf2 => output1=mf5 (1)"
3	"input1==mf3 => output1=mf3 (1)"
4	"input1==mf4 => output1=mf1 (1)"
5	"input1==mf5 => output1=mf2 (1)"

In this case, the tuning process bypasses the invalid values and uses only valid parameter values for optimization.

By default, `tunefis` ignores invalid values when updating fuzzy system parameters. You can change this behavior by setting `tunefisOptions.IgnoreInvalidParameters` to `false`.

Custom Functions

```
function cost = customcostfcn(fis,x,y)
```

```
tY = evalfis(fis,x);
sincosx = tY(:,1)+tY(:,2);
sincosexpx = sincosx.*tY(:,3);
actY = [sincosx;sincosexpx];
d = y(:)-actY;
```

```

cost = sqrt(mean(d.*d));

end

function fis = customtunefis(fis,rule,x,y,n,ignore)

% Show the initial cost.
cost = findcost(fis,x,y);
fprintf('Initial cost = %f\n',cost);

% Optimize the rule parameters.
numMFs = numel(fis.Outputs.MembershipFunctions);
for ite = 1:n
    for i = 1:numel(rule)
        % Get the consequent value.
        pval = getTunableValues(fis,rule(i));
        % Loop through the output MF indices to minimize the cost.
        % Use the output indices according to AllowNot and AllowEmpty.
        allowNot = rule(i).Consequent.AllowNot;
        allowEmpty = rule(i).Consequent.AllowEmpty;
        if allowNot && allowEmpty
            mfID = -numMFs:numMFs;
        elseif allowNot && ~allowEmpty
            mfID = [-numMFs:-1 1:numMFs];
        elseif ~allowNot && allowEmpty
            mfID = 0:numMFs;
        else
            mfID = 1:numMFs;
        end
        cost = 1000;
        minCostFIS = fis;
        for j = 1:length(mfID)
            % Update the consequent value.
            pval(1) = mfID(j);
            % Set the consequent value in the FIS.
            fis = setTunableValues(fis,rule(i),pval,'IgnoreInvalidParameters',ignore);
            % Evaluate cost.
            rmse = findcost(fis,x,y);
            % Update the FIS with the minimum cost.
            if rmse < cost
                cost = rmse;
                minCostFIS = fis;
            end
        end
        fis = minCostFIS;
    end
    fprintf('Iteration %d: Cost = %f\n',ite,cost);
end

end

function cost = findcost(fis,x,y)

actY = evalfis(fis,x);
d = y - actY;
cost = sqrt(mean(d.*d));

```

end

See Also

tunefis | getTunableSettings

More About

- “Tune Mamdani Fuzzy Inference System” on page 3-28
- “Tune Fuzzy Trees” on page 3-15

Tune Mamdani Fuzzy Inference System

This example shows how to tune membership function (MF) and rule parameters of a Mamdani fuzzy inference system (FIS). This example uses particle swarm and pattern search optimization, which require Global Optimization Toolbox™ software.

Automobile fuel consumption prediction in miles per gallon (MPG) is a typical nonlinear regression problem. It uses several automobile profile attributes to predict fuel consumption. The training data is available in the University of California at Irvine Machine Learning Repository and contains data collected from automobiles of various makes and models.

This example uses the following six input data attributes to predict the output data attribute MPG with a FIS:

- 1 Number of cylinders
- 2 Displacement
- 3 Horsepower
- 4 Weight
- 5 Acceleration
- 6 Model year

Prepare Data

Load the data. Each row of the dataset obtained from the repository represents a different automobile profile.

```
[data,name] = loadGasData;
```

Remove leading and trailing whitespace from the attribute names.

```
name = strtrim(string(name));
```

`data` contains 7 columns, where the first six columns contain the following input attributes.

- Number of cylinders
- Displacement
- Horsepower
- Weight
- Acceleration
- Model year

The seventh column contains the output attribute, MPG.

Create separate input and output data sets, `X` and `Y`, respectively.

```
X = data(:,1:6);  
Y = data(:,7);
```

Partition the input and output data sets into training data (odd-indexed samples) and validation data (even-indexed samples).

```
trnX = X(1:2:end,:); % Training input data set  
trnY = Y(1:2:end,:); % Training output data set
```

```
vldX = X(2:2:end,:); % Validation input data set
vldY = Y(2:2:end,:); % Validation output data set
```

Extract the range of each data attribute, which you will use for input/output range definition during FIS construction.

```
dataRange = [min(data)' max(data)'];
```

Construct FIS using Data Attribute Ranges

Create a Mamdani FIS for tuning.

```
fisin = mamfis;
```

Add input and output variables to the FIS, where each variable represents one of the data attributes. For each variable, use the corresponding attribute name and range.

To reduce the number of rules, use two MFs for each input variable, which results in $2^6 = 64$ input MF combinations. Therefore, the FIS uses a maximum of 64 rules corresponding to the input MF combinations.


To improve data generalization beyond the training data, use 64 MFs for the output variable. Doing so allows the FIS to use a different output MF for each rule.

Both input and output variables use default triangular MFs, which are uniformly distributed over the variable ranges.

```
for i = 1:6
    fisin = addInput(fisin,dataRange(i,:), 'Name', name(i), 'NumMFs', 2);
end
fisin = addOutput(fisin,dataRange(7,:), 'Name', name(7), 'NumMFs', 64);
```

View the FIS structure. Initially, the FIS has zero rules. The rules of the system are found during the tuning process.

```
figure
plotfis(fisin)
```



System fis: 6 inputs, 1 outputs, 0 rules

Tune FIS with Training Data

Tuning is performed in two steps.

- 1 Learn the rule base while keeping the input and output MF parameters constant.
- 2 Tune the parameters of the input/output MFs and rules.

The first step is less computationally expensive due to the small number of rule parameters, and it quickly converges to a fuzzy rule base during training. In the second step, using the rule base from the first step as an initial condition provides fast convergence of the parameter tuning process.

Learn Rules

To learn a rule base, first specify tuning options using a `tunefisOptions` object. Since the FIS allows a large number of output MFs (used in rule consequents), use a global optimization method (genetic algorithm or particle swarm). Such methods perform better in large parameter tuning ranges as compared to local optimization methods (pattern search and simulation annealing). For this example, tune the FIS using the particle swarm optimization method (`'particleswarm'`).

To learn new rules, set the `OptimizationType` to `'learning'`. Restrict the maximum number of rules to 64. The number of tuned rules can be less than this limit, since the tuning process removes duplicate rules.

```
options = tunefisOptions('Method','particleswarm',...
    'OptimizationType','learning', ...
    'NumMaxRules',64);
```


If you have Parallel Computing Toolbox™ software, you can improve the speed of the tuning process by setting `options.UseParallel` to `true`. If you do not have Parallel Computing Toolbox software, set `options.UseParallel` to `false`.

Set the maximum number of iterations to 20. To reduce training error in the rule learning process, you can increase the number of iterations. However, using too many iterations can overtune the FIS to the training data, increasing the validation errors.

```
options.MethodOptions.MaxIterations = 20;
```

Since particle swarm optimization uses random search, to obtain reproducible results, initialize the random number generator to its default configuration.

```
rng('default')
```

Tune the FIS using the specified tuning data and options.

Learning rules using the `tunefis` function takes approximately 5 minutes. For this example, enable tuning by setting `runtunefis` to `true`. To load pretrained results without running `tunefis`, you can set `runtunefis` to `false`.

```
runtunefis = false;
```

Parameter settings can be empty when learning new rules. For more information, see `tunefis`.


```
if runtunefis
    fisout1 = tunefis(fisin,[],trnX,trnY,options); %#ok<UNRCH>
else
    tunedfis = load('tunedfismpgprediction.mat');
    fisout1 = tunedfis.fisout1;
    fprintf('Training RMSE = %.3f MPG\n',calculateRMSE(fisout1,trnX,trnY));
end
```

```
Training RMSE = 4.452 MPG
```

The **Best f(x)** column shows the training root-mean-squared-error (RMSE).

View the structure of the tuned FIS, `fisout1`.

```
plotfis(fisout1)
```



System fis: 6 inputs, 1 outputs, 61 rules

The learning process produces a set of new rules for the FIS. For example, view the descriptions of the first three rules.


```
[fisout1.Rules(1:3).Description]'
```

```
ans = 3x1 string
    "Cylinder==mf2 & Disp==mf2 & Power==mf2 & Weight==mf2 & Year==mf2 => MPG=mf5 (1)"
    "Cylinder==mf1 & Power==mf2 & Weight==mf2 & Acceler==mf2 & Year==mf1 => MPG=mf63 (1)"
    "Cylinder==mf2 & Disp==mf1 & Acceler==mf2 => MPG=mf28 (1)"
```

The learned system should have similar RMSE performance for both the training and validation data sets. To calculate the RMSE for the validation data set, evaluate `fisout1` using validation input data set `vldX`. To hide run-time warnings during evaluation, set all the warning options to none.

Calculate the RMSE between the generated output data and the validation output data set `vldY`.

```
plotActualAndExpectedResultsWithRMSE(fisout1,vldX,vldY)
```



Since the training and validation errors are similar, the learned system does not overfit the training data.

Tune All Parameters

After learning the new rules, tune the input/output MF parameters along with the parameters of the learned rules. To obtain the tunable parameters of the FIS, use the `getTunableSettings` function.

```
[in,out,rule] = getTunableSettings(fisout1);
```

To tune the existing FIS parameter settings without learning new rules, set the `OptimizationType` to 'tuning'.

```
options.OptimizationType = 'tuning';
```

Since the FIS already learned rules using the training data, use a local optimization method for fast convergence of the parameter values. For this example, use the pattern search optimization method ('patternsearch').

```
options.Method = 'patternsearch';
```

Tuning the FIS parameters takes more iterations than the previous rule-learning step. Therefore, increase the maximum number of iterations of the tuning process to 60. As in the first tuning stage, you can reduce training errors by increasing the number of iterations. However, using too many iterations can overtune the parameters to the training data, increasing the validation errors.

```
options.MethodOptions.MaxIterations = 60;
```

To improve pattern search results, set method option `UseCompletePoll` to true.

```
options.MethodOptions.UseCompletePoll = true;
```

Tune the FIS parameters using the specified tunable settings, training data, and tuning options.


Tuning parameter values with `tunefis` function takes approximately 5 minutes. To load pretrained results without running `tunefis`, you can set `runtunefis` to false.

```
if runtunefis
    rng('default') %#ok<UNRCH>
    fisout = tunefis(fisout1,[in;out;rule],trnX,trnY,options);
else
    fisout = tunedfis.fisout;
    fprintf('Training RMSE = %.3f MPG\n',calculateRMSE(fisout,trnX,trnY));
end
```

```
Training RMSE = 2.903 MPG
```

At the end of the tuning process, some of the tuned MF shapes are different than the original ones.

```
figure
plotfis(fisout)
```




System fis: 6 inputs, 1 outputs, 61 rules

Check Performance

Validate the performance of the tuned FIS, `fisout`, using the validation input data set `vldX`.

Compare the expected MPG obtained from the validation output data set `vldY` and actual MPG generated using `fisout`. Compute the RMSE between these results.

```
plotActualAndExpectedResultsWithRMSE(fisout,vldX,vldY);
```



Tuning the FIS parameters improves the RMSE compared to the results from the initial learned rule base. Since the training and validation errors are similar, the parameters values are not overtuned.

Conclusion

You can further improve the training error of the tuned FIS by:

- Increasing number of iterations in both the rule-learning and parameter-tuning phases. Doing so increases the duration of the optimization process and can also increase validation error due to overtuned system parameters with the training data.
- Using global optimization methods, such as `ga` and `particleswarm`, in both rule-learning and parameter-tuning phases. `ga` and `particleswarm` perform better for large parameter tuning ranges since they are global optimizers. On the other hand, `patternsearch` and `simulannealbnd` perform better for small parameter ranges since they are local optimizers. If a FIS is generated from training data with `genfis` or a rule base is already added to a FIS using training data, then `patternsearch` and `simulannealbnd` may produce faster convergence as compared to `ga` and `particleswarm`. For more information on these optimization methods and their options, see `ga` (Global Optimization Toolbox), `particleswarm` (Global Optimization Toolbox), `patternsearch` (Global Optimization Toolbox), and `simulannealbnd` (Global Optimization Toolbox).

- Changing the FIS properties, such as the type of FIS, number of inputs, number of input/output MFs, MF types, and number of rules. For fuzzy systems with a large number of inputs, a Sugeno FIS generally converges faster than a Mamdani FIS since a Sugeno system has fewer output MF parameters (if constant MFs are used) and faster defuzzification. Small numbers of MFs and rules reduce the number of parameters to tune, producing a faster tuning process. Furthermore, a large number of rules may overfit the training data. In general, for larger fuzzy systems, a FIS tree can produce similar performance with a smaller number of rules as compared to a single FIS. For an example, see “Tune FIS Tree for Gas Mileage Prediction” on page 3-38.
- Modifying tunable parameter settings for MFs and rules. For example, you can tune the support of a triangular MF without changing its peak location. Doing so reduces the number of tunable parameters and can produce a faster tuning process for specific applications. For rules, you can exclude zero MF indices by setting the AllowEmpty tunable setting to false, which reduces the overall number of rules during the learning phase.

Local Functions

```
function plotActualAndExpectedResultsWithRMSE(fis,x,y)

% Calculate RMSE between actual and expected results
[rmse,actY] = calculateRMSE(fis,x,y);

% Plot results
figure
subplot(2,1,1)
hold on
bar(actY)
bar(y)
bar(min(actY,y),'FaceColor',[0.5 0.5 0.5])
hold off
axis([0 200 0 60])
xlabel("Validation input dataset index"),ylabel("MPG")
legend(["Actual MPG" "Expected MPG" "Minimum of actual and expected values"],...
        'Location','NorthWest')
title("RMSE = " + num2str(rmse) + " MPG")

subplot(2,1,2)
bar(actY-y)
xlabel("Validation input dataset index"),ylabel("Error (MPG)")
title("Difference Between Actual and Expected Values")

end

function [rmse,actY] = calculateRMSE(fis,x,y)

% Specify options for FIS evaluation
persistent evalOptions
if isempty(evalOptions)
    evalOptions = evalfisOptions("EmptyOutputFuzzySetMessage","none", ...
        "NoRuleFiredMessage","none","OutOfRangeInputValueMessage","none");
end

% Evaluate FIS
actY = evalfis(fis,x,evalOptions);

% Calculate RMSE
del = actY - y;
```

```
rmse = sqrt(mean(del.^2));
```

```
end
```

See Also

[tunefis](#) | [getTunableSettings](#) | [genfis](#)

More About

- “Tune Mamdani Fuzzy Inference System” on page 3-28
- “Tune FIS Tree for Gas Mileage Prediction” on page 3-38

Tune FIS Tree for Gas Mileage Prediction

This example shows how to tune parameters of a FIS tree, which is a collection of connected fuzzy inference systems. This example uses particle swarm and pattern search optimization, which require Global Optimization Toolbox™ software.

Automobile fuel consumption prediction in miles per gallon (MPG) is a typical nonlinear regression problem. It uses several automobile profile attributes to predict fuel consumption. The training data is available in the University of California at Irvine Machine Learning Repository and contains data collected from automobiles of various makes and models.

This example uses the following six input data attributes to predict the output data attribute MPG with a FIS tree:

- 1 Number of cylinders
- 2 Displacement
- 3 Horsepower
- 4 Weight
- 5 Acceleration
- 6 Model year

Prepare Data

Load the data. Each row of the dataset obtained from the repository represents a different automobile profile.

```
data = loadGasData;
```

data contains 7 columns, where the first six columns contain the following input attributes.

- Number of cylinders
- Displacement
- Horsepower
- Weight
- Acceleration
- Model year

The seventh column contains the output attribute, MPG.

Create separate input and output data sets, X and Y, respectively.

```
X = data(:,1:6);  
Y = data(:,7);
```

Partition the input and output data sets into training data (odd-indexed samples) and validation data (even-indexed samples).

```
trnX = X(1:2:end,:); % Training input data set  
trnY = Y(1:2:end,:); % Training output data set  
vldX = X(2:2:end,:); % Validation input data set  
vldY = Y(2:2:end,:); % Validation output data set
```


Extract the range of each data attribute, which you will use for input/output range definition during FIS construction.

```
dataRange = [min(data)' max(data)'];
```

Construct a FIS Tree

For this example, construct a FIS tree using the following steps:

- 1 Rank the input attributes based on their correlations with the output attribute.
- 2 Create multiple FIS objects using the ranked input attributes.
- 3 Construct a FIS tree from the FIS objects.

Rank Inputs According to Correlation Coefficients

Calculate the correlation coefficients for the training data. In the final row of the correlation matrix, the first six elements show the correlation coefficients between the six put data attributes and the output attribute.

```
c1 = corrcoef(data);
c1(end, :)
```

```
ans = 1×7
```

```
-0.7776 -0.8051 -0.7784 -0.8322 0.4233 0.5805 1.0000
```

The first four input attributes have negative values, and the last two input attributes have positive values.

Rank the input attributes that have negative correlations in descending order by the absolute value of their correlation coefficients.

- 1 Weight
- 2 Displacement
- 3 Horsepower
- 4 Number of cylinders


Rank the input attributes that have positive correlations in descending order by the absolute value of their correlation coefficients.

- 1 Model year
- 2 Acceleration

These rankings show that the weight and model year have the highest negative and positive correlations with MPG, respectively.

Create Fuzzy Inference Systems

For this example, implement a FIS tree with the following structure.



The FIS tree uses multiple two-input-one-output FIS objects to reduce the total number of rules used in the inference process. `fis1`, `fis2`, and `fis3` directly take the input values and generate intermediate MPG values, which are further combined using `fis4` and `fis5`.

Input attributes with negative and positive correlation values are paired up to combine both positive and negative effects on the output for prediction. The inputs are grouped according to their ranks as follows:

- Weight and model year
- Displacement and acceleration
- Horsepower and number of cylinders

The last group includes only inputs with negative correlation values since there are only two inputs with positive correlation values.

This example uses Sugeno-type FIS objects for faster evaluation during the tuning process as compared to Mamdani systems. Each FIS includes two inputs and one output, where each input contains two default triangular membership functions (MFs), and the output includes 4 default constant MFs. Specify the input and output ranges using the corresponding data attribute ranges.

The first FIS combines the weight and model year attributes.

```

fis1 = sugfis('Name', 'fis1');
fis1 = addInput(fis1, dataRange(4, :), 'NumMFs', 2, 'Name', "weight");
fis1 = addInput(fis1, dataRange(6, :), 'NumMFs', 2, 'Name', "year");
fis1 = addOutput(fis1, dataRange(7, :), 'NumMFs', 4);
  
```

The second FIS combines the displacement and acceleration attributes.

```

fis2 = sugfis('Name', 'fis2');
fis2 = addInput(fis2, dataRange(2, :), 'NumMFs', 2, 'Name', "displacement");
fis2 = addInput(fis2, dataRange(5, :), 'NumMFs', 2, 'Name', "acceleration");
fis2 = addOutput(fis2, dataRange(7, :), 'NumMFs', 4);
  
```

The third FIS combines the horsepower and number of cylinder attributes.

```

fis3 = sugfis('Name', 'fis3');
fis3 = addInput(fis3, dataRange(3, :), 'NumMFs', 2, 'Name', "horsepower");
fis3 = addInput(fis3, dataRange(1, :), 'NumMFs', 2, 'Name', "cylinders");
fis3 = addOutput(fis3, dataRange(7, :), 'NumMFs', 4);
  
```

The fourth FIS combines the outputs of the first and second FIS.

```

fis4 = sugfis('Name','fis4');
fis4 = addInput(fis4,dataRange(7,:), 'NumMFs',2);
fis4 = addInput(fis4,dataRange(7,:), 'NumMFs',2);
fis4 = addOutput(fis4,dataRange(7,:), 'NumMFs',4);

```

The final FIS combines the outputs of third and fourth FIS and generates the estimated MPG. This FIS has the same input and output ranges as the fourth FIS.

```

fis5 = fis4;
fis5.Name = 'fis5';
fis5.Outputs(1).Name = "mpg";

```

Construct FIS Tree

Connect the fuzzy systems (fis1, fis2, fis3, fis4, and fis5) according to the FIS tree diagram.

```

fisTin = fistree([fis1 fis2 fis3 fis4 fis5],[ ...
    "fis1/output1" "fis4/input1"; ...
    "fis2/output1" "fis4/input2"; ...
    "fis3/output1" "fis5/input2"; ...
    "fis4/output1" "fis5/input1"])

```

```

fisTin =
    fistree with properties:

```

```

        Name: "fistreemodel"
        FIS: [1x5 sugfis]
    Connections: [4x2 string]
        Inputs: [6x1 string]
        Outputs: "fis5/mpg"

```

```

    DisableStructuralChecks: 0

```

See 'getTunableSettings' method for parameter optimization.

Tune FIS Tree with Training Data

Tuning is performed in two steps.

- 1 Learn the rule base while keeping the input and output MF parameters constant.
- 2 Tune the parameters of the input/output MFs and rules.

The first step is less computationally expensive due to the small number of rule parameters, and it quickly converges to a fuzzy rule base during training. In the second step, using the rule base from the first step as an initial condition provides fast convergence of the parameter tuning process.

Learn Rules

To learn a rule base, first specify tuning options using a `tunefisOptions` object. Global optimization methods (genetic algorithm or particle swarm) are suitable for initial training when all the parameters of a fuzzy system are untuned. For this example, tune the FIS tree using the particle swarm optimization method ('particleswarm').

To learn new rules, set the `OptimizationType` to 'learning'. Restrict the maximum number of rules to 4. The number of tuned rules of each FIS can be less than this limit, since the tuning process removes duplicate rules.

```
options = tunefisOptions('Method','particleswarm',...
    'OptimizationType','learning', ...
    'NumMaxRules',4);
```

If you have Parallel Computing Toolbox™ software, you can improve the speed of the tuning process by setting `options.UseParallel` to `true`. If you do not have Parallel Computing Toolbox software, set `options.UseParallel` to `false`.

Set the maximum number of iterations to 50. To reduce training error in the rule learning process, you can increase the number of iterations. However, using too many iterations can overtune the FIS tree to the training data, increasing the validation errors.

```
options.MethodOptions.MaxIterations = 50;
```

Since particle swarm optimization uses random search, to obtain reproducible results, initialize the random number generator to its default configuration.

```
rng('default')
```

Tune the FIS tree using the specified tuning data and options. Set the input order of the training data according to the FIS tree connections as follows: weight, year, displacement, acceleration, horsepower, and cylinders.

```
inputOrders1 = [4 6 2 5 3 1];
orderedTrnX1 = trnX(:,inputOrders1);
```

Learning rules with `tunefis` function takes approximately 4 minutes. For this example, enable tuning by setting `runtunefis` to `true`. To load pretrained results without running `tunefis`, you can set `runtunefis` to `false`.

```
runtunefis = false;
```

Parameter settings can be empty when learning new rules. For more information, see `tunefis`.

```
if runtunefis
    fisTout1 = tunefis(fisTin,[],orderedTrnX1,trnY,options); %#ok<UNRCH>
else
    tunedfis = load('tunedfistreempgprediction.mat');
    fisTout1 = tunedfis.fisTout1;
    rmseValue = calculateRMSE(fisTout1,orderedTrnX1,trnY);
    fprintf('Training RMSE = %.3f MPG\n',rmseValue);
end
```

```
Training RMSE = 3.399 MPG
```

The Best `f(x)` column shows the training root-mean-squared-error (RMSE).

The learning process produces a set of new rules for the FIS tree.


```
fprintf("Total number of rules = %d\n",numel([fisTout1.FIS.Rules]));
```

```
Total number of rules = 17
```

The learned system should have similar RMSE performance for both the training and validation data sets. To calculate the RMSE for the validation data set, evaluate `fisout1` using validation input data set `vldX`. To hide run-time warnings during evaluation, set all the warning options to `none`.

Calculate the RMSE between the generated output data and the validation output data set `vldY`. Since the training and validation errors are similar, the learned system does not overfit the training data.

```
orderedVldX1 = vldX(:,inputOrders1);
plotActualAndExpectedResultsWithRMSE(fisTout1,orderedVldX1,vldY)
```



Tune All Parameters

After learning the new rules, tune the input/output MF parameters along with the parameters of the learned rules. To obtain the tunable parameters of the FIS tree, use the `getTunableSettings` function.

```
[in,out,rule] = getTunableSettings(fisTout1);
```

To tune the existing FIS tree parameter settings without learning new rules, set the `OptimizationType` to 'tuning'.

```
options.OptimizationType = 'tuning';
```

Since the FIS tree already learned rules using the training data, use a local optimization method for fast convergence of the parameter values. For this example, use the pattern search optimization method ('patternsearch').

```
options.Method = 'patternsearch';
```

Tuning the FIS tree parameters takes more iterations than the previous rule-learning step. Therefore, increase the maximum number of iterations of the tuning process to 75. As in the first tuning stage,

you can reduce training errors by increasing the number of iterations. However, using too many iterations can overtune the parameters to the training data, increasing the validation errors.

```
options.MethodOptions.MaxIterations = 75;
```

To improve pattern search results, set method option `UseCompletePoll` to true.

```
options.MethodOptions.UseCompletePoll = true;
```

Tune the FIS tree parameters using the specified tunable settings, training data, and tuning options.

Tuning parameter values with `tunefis` function takes several minutes. To load pretrained results without running `tunefis`, you can set `runtunefis` to false.

```
rng('default')
if runtunefis
    fisTout2 = tunefis(fisTout1,[in;out;rule],orderedTrnX1,trnY,options); %#ok<UNRCH>
else
    fisTout2 = tunedfis.fisTout2;
    rmseValue = calculateRMSE(fisTout2,orderedTrnX1,trnY);
    fprintf('Training RMSE = %.3f MPG\n',rmseValue);
end
```

```
Training RMSE = 3.037 MPG
```


At the end of the tuning process, the training error reduces compared to the previous step.

Check Performance

Validate the performance of the tuned FIS tree, `fisout2`, using the validation input data set `vldX`.

Compare the expected MPG obtained from the validation output data set `vldY` and actual MPG generated using `fisout2`. Compute the RMSE between these results.

```
plotActualAndExpectedResultsWithRMSE(fisTout2,orderedVldX1,vldY)
```



Tuning the FIS tree parameters improves the RMSE compared to the results from the initial learned rule base. Since the training and validation errors are similar, the parameters values are not overtuned.

Analyze Intermediate Data

To gain insight into the operation of your fuzzy tree, you can add the outputs of the component fuzzy systems as outputs of your FIS tree. For this example, to access the intermediate FIS outputs, add three additional outputs to the tuned FIS tree.

```

fisTout3 = fisTout2;
fisTout3.Outputs(end+1) = "fis1/output1";
fisTout3.Outputs(end+1) = "fis2/output1";
fisTout3.Outputs(end+1) = "fis3/output1";


```

To generate the additional outputs, evaluate the augmented FIS tree, `fisTout3`.

```

actY = evaluateFIS(fisTout3,orderedVldX1);
figure
plot(actY(:,[2 3 4 1]))
xlabel("Input dataset index")
ylabel("MPG"),axis([1 200 0 55])
legend(["Output of fis1" "Output of fis2" "Output of fis3" "Output of fis5"],...
'Location','NorthEast','NumColumns',2)
title("Intermediate and Final Outputs")

```



The final output of the FIS tree (fis5 output) appears to be highly correlated with the outputs of fis1 and fis3. To validate this assessment, check the correlation coefficients of the FIS outputs.

```
c2 = corrcoef(actY(:,[2 3 4 1]));
c2(end,:)


ans = 1×4

    0.9541    0.8245   -0.8427    1.0000
```

The last row of the correlation matrix shows that the outputs of fis1 and fis3 (first and third column, respectively) have higher correlations with the final output as compared to the output of fis2 (second column). This result indicates that simplifying the FIS tree by removing fis2 and fis4 and can potentially produce similar training results compared to the original tree structure.

Simplify and Retrain FIS Tree

Remove fis2 and fis4 from the FIS tree and connect the output of fis1 to the first input of fis5. When you remove a FIS from a FIS tree, any existing connections to that FIS are also removed.



```

fisTout3.FIS([2 4]) = [];
fisTout3.Connections(end+1,:) = ["fis1/output1" "fis5/input1"];
fis5.Inputs(1).Name = "fis1out";

```

To make the number of FIS tree outputs match the number of outputs in the training data, remove the FIS tree outputs from `fis1` and `fis3`.

```

fisTout3.Outputs(2:end) = [];

```

Update the input training data order according to the new FIS tree input configuration.

```

inputOrders2 = [4 6 3 1];
orderedTrnX2 = trnX(:,inputOrders2);

```

Since the FIS tree configuration is changed, you must rerun both the learning and tuning steps. In the learning phase, the existing rule parameters are also tuned to fit the new configuration of the FIS tree.

```

options.Method = "particleswarm";
options.OptimizationType = "learning";
options.MethodOptions.MaxIterations = 50;

[~,~,rule] = getTunableSettings(fisTout3);

rng('default')
if runtunefis
    fisTout4 = tunefis(fisTout3,rule,orderedTrnX2,trnY,options); %#ok<UNRCH>
else
    fisTout4 = tunedfis.fisTout4;
    rmseValue = calculateRMSE(fisTout4,orderedTrnX2,trnY);
    fprintf('Training RMSE = %.3f MPG\n',rmseValue);
end

```

```

Training RMSE = 3.380 MPG

```

In the training phase, the parameters of the membership function and rules are tuned.

```

options.Method = "patternsearch";
options.OptimizationType = "tuning";
options.MethodOptions.MaxIterations = 75;
options.MethodOptions.UseCompletePoll = true;
[in,out,rule] = getTunableSettings(fisTout4);
rng('default')
if runtunefis

```

```

    fisTout5 = tunefis(fisTout4,[in;out;rule],orderedTrnX2,trnY,options); %#ok<UNRCH>
else
    fisTout5 = tunedfis.fisTout5;
    rmseValue = calculateRMSE(fisTout5,orderedTrnX2,trnY);
    fprintf('Training RMSE = %.3f MPG\n',rmseValue);
end

```

Training RMSE = 3.049 MPG

At the end of the tuning process, the FIS tree contains updated MF and rule parameter values. The rule base size of the new FIS tree configuration is smaller than the previous configuration.


```
fprintf("Total number of rules = %d\n",numel([fisTout5.FIS.Rules]));
```

Total number of rules = 11

Check Performance of the Simplified FIS Tree

Evaluate the updated FIS tree using the four input attributes of the checking dataset.

```
orderedVldX2 = vldX(:,inputOrders2);
plotActualAndExpectedResultsWithRMSE(fisTout5,orderedVldX2,vldY)
```



The simplified FIS tree with four input attributes produces better results in terms of RMSE as compared to the first configuration, which uses six input attributes. Therefore, it shows that a FIS tree can be represented with fewer number of inputs and rules to generalize the training data.

Conclusion

You can further improve the training error of the tuned FIS tree by:

- Increasing number of iterations in both the rule-learning and parameter-tuning phases. Doing so increases the duration of the optimization process and can also increase validation error due to overtuned system parameters with the training data.
- Using global optimization methods, such as `ga` and `particleswarm`, in both rule-learning and parameter-tuning phases. `ga` and `particleswarm` perform better for large parameter tuning ranges since they are global optimizers. On the other hand, `patternsearch` and `simulannealbnd` perform better for small parameter ranges since they are local optimizers. If rules are already added to a FIS tree using training data, then `patternsearch` and `simulannealbnd` may produce faster convergence as compared to `ga` and `particleswarm`. For more information on these optimization methods and their options, see `ga` (Global Optimization Toolbox), `particleswarm` (Global Optimization Toolbox), `patternsearch` (Global Optimization Toolbox), and `simulannealbnd` (Global Optimization Toolbox).
- Changing the FIS properties, such as the type of FIS, number of inputs, number of input/output MFs, MF types, and number of rules. For fuzzy systems with a large number of inputs, a Sugeno FIS generally converges faster than a Mamdani FIS since a Sugeno system has fewer output MF parameters (if constant MFs are used) and faster defuzzification. Small numbers of MFs and rules reduce the number of parameters to tune, producing a faster tuning process. Furthermore, a large number of rules may overfit the training data.
- Modifying tunable parameter settings for MFs and rules. For example, you can tune the support of a triangular MF without changing its peak location. Doing so reduces the number of tunable parameters and can produce a faster tuning process for specific applications. For rules, you can exclude zero MF indices by setting the `AllowEmpty` tunable setting to `false`, which reduces the overall number of rules during the learning phase.
- Changing FIS tree properties, such as number of fuzzy systems and connections between the fuzzy systems.
- Using different ranking and grouping of the inputs to the FIS tree.

Local Functions

```
function plotActualAndExpectedResultsWithRMSE(fis,x,y)

% Calculate RMSE between actual and expected results
[rmse,actY] = calculateRMSE(fis,x,y);

% Plot results
figure
subplot(2,1,1)
hold on
bar(actY)
bar(y)
bar(min(actY,y),'FaceColor',[0.5 0.5 0.5])
hold off
axis([0 200 0 60])
xlabel("Validation input dataset index"),ylabel("MPG")
legend(["Actual MPG" "Expected MPG" "Minimum of actual and expected values"],...
'Location','NorthWest')
title("RMSE = " + num2str(rmse) + " MPG")

subplot(2,1,2)
bar(actY-y)
```

```
xlabel("Validation input dataset index"),ylabel("Error (MPG)")
title("Difference Between Actual and Expected Values")

end

function [rmse,actY] = calculateRMSE(fis,x,y)

% Evaluate FIS
actY = evaluateFIS(fis,x);

% Calculate RMSE
del = actY - y;
rmse = sqrt(mean(del.^2));

end

function y = evaluateFIS(fis,x)

% Specify options for FIS evaluation
persistent evalOptions
if isempty(evalOptions)
    evalOptions = evalfisOptions("EmptyOutputFuzzySetMessage","none", ...
        "NoRuleFiredMessage","none","OutOfRangeInputValueMessage","none");
end

% Evaluate FIS
y = evalfis(fis,x,evalOptions);

end
```

See Also

tunefis | sugfis | getTunableSettings | fistree

More About

- “Tuning Fuzzy Inference Systems” on page 3-2
- “Tune Mamdani Fuzzy Inference System” on page 3-28


Optimize FIS Parameters with k-Fold Cross-Validation

This example shows how to optimize the parameters of a fuzzy inference system (FIS) using k-fold cross-validation. This example uses genetic algorithm (GA) optimization.

Data Overfitting in FIS Parameter Tuning

Data overfitting is a common problem in FIS parameter optimization. When overfitting occurs, the tuned FIS produces optimized results for the training data set but performs poorly for a test data set. Due to overtuning, the optimized FIS parameter values pick up noise from the training data set and lose the ability to generalize to new data sets. The difference between the training and test performance increases with the increased bias of the training data set.

To overcome the data overfitting problem, you can stop a tuning process early based on an unbiased evaluation of the model using a separate validation data set. However, such a validation data set can also increase bias if it does not accurately represent the problem space. To overcome bias from the validation data set, a k-fold cross-validation approach is commonly used. Here, the training data is randomly shuffled and then divided into k partitions, as shown in the following figure. For each training-validation iteration, you use a different partition for validation, and use the remaining data for testing. Therefore, you use each data partition once for validation and $k - 1$ times for training.



Each training-validation iteration runs for n cycles. However, an iteration can stop early and advance to the next iteration if an increase in the validation cost exceeds a predefined threshold value. The optimized model at the end of the k^{th} iteration is used as the output of the k-fold cross-validation process.

This example shows how using k-fold cross-validation with the `tunefis` function prevents data overfitting compared to parameter tuning that does not use k-fold cross-validation.

Tune FIS Without K-Fold Validation

This example describes a data overfitting problem for automobile fuel consumption prediction. It uses several automobile profile attributes to predict fuel consumption. The training data is available in the

University of California at Irvine Machine Learning Repository and contains data collected from automobiles of various makes and models.

This example uses the following six input data attributes to predict the output data attribute MPG with a FIS.

- Number of cylinders
- Displacement
- Horsepower
- Weight
- Acceleration
- Model year

Load the data using the `loaddata` utility function shown at the end of the example. This function creates training and test data sets.

```
[data,varName,trnX,trnY,testX,testY] = loadData;
```

Create an initial FIS based on the input and output data attributes using the `constructFIS` utility function.

```
fisin = constructFIS(data,varName);
```

Create an option set for tuning the FIS. The default option set uses GA for optimization.

```
options = tunefisOptions;
```

If you have Parallel Computing Toolbox™ software, you can improve the speed of the tuning process by setting `options.UseParallel` to `true`. If you do not have Parallel Computing Toolbox software, set `options.UseParallel` to `false`.

To demonstrate the data overfitting problem, this example uses a maximum of 100 generations to tune the rules.

```
options.MethodOptions.MaxGenerations = 100;
```

Tune the FIS using the specified tuning data and options. Tuning rules using the `tunefis` function takes several minutes. This example uses a flag, `runtunefis`, to either run the `tunefis` function or load pretrained results. To load the pretrained results, set `runtunefis` to `false`.

```
runtunefis = false;
```

To demonstrate the data overfitting problem, use the following performance measures:

- Training error — Root mean squared error (RMSE) between the expected training output and the actual training output obtained from the tuned FIS.
- Test error — RMSE between the expected test output and the actual test output obtained from the tuned FIS.
- Function count — Total number of evaluations of the cost function for tuning the FIS.

In this example, use only rule parameter settings to tune the FIS.

Since GA optimization uses random search, to obtain reproducible results, initialize the random number generator to its default configuration.

```

if runtunefis
    % Get rule parameter settings.
    [~,~,rule] = getTunableSettings(fisin);

    % Set default random number generator.
    rng('default')

    % Tune rule parameters.
    [outputFIS,optimData] = tunefis(fisin,rule,trnX,trnY,options);

    % Get the training error.
    trnErrNoKFold = optimData.tuningOutputs.fval

    % Calculate the test error.
    evalOptions = evalfisOptions("EmptyOutputFuzzySetMessage","none", ...
        "NoRuleFiredMessage","none","OutOfRangeInputValueMessage","none");
    actY = evalfis(outputFIS,testX,evalOptions);
    del = actY - testY;
    testErrNoKFold = sqrt(mean(del.^2))

    % Get the function count.
    fcnCountNoKFold = optimData.totalFcnCount

    save tuningWithoutKFoldValidation trnErrNoKFold testErrNoKFold fcnCountNoKFold
else
    % Load the pretrained results.
    results = load('tuningWithoutKFoldValidation.mat');
    trnErrNoKFold = results.trnErrNoKFold
    testErrNoKFold = results.testErrNoKFold
    fcnCountNoKFold = results.fcnCountNoKFold
end

trnErrNoKFold = 2.4952

testErrNoKFold = 2.8412

fcnCountNoKFold = 19210

```

The higher value of the test error compared to the training error indicates that the trained FIS is more biased to the training data.

Tune FIS Parameters with K-Fold Validation

You can use k-fold cross-validation in FIS parameter optimization by setting `options.KFoldValue` to a value greater than or equal to 2. For this example, set the k-fold value to 4.

```
options.KFoldValue = 4;
```

To specify a tolerance value, used to stop the k-fold tuning process early, set the `options.ValidationTolerance` property. For this example, set the tolerance value to 0.02. This tolerance value configures the k-fold tuning process to stop if the current validation cost increases by more than 2% of the minimum validation cost found up to that point in the tuning process.

```
options.ValidationTolerance = 0.02;
```

For a noisy data set, you can compute a moving average of the validation cost by setting the `options.ValidationWindowSize` property to a value greater than 1. For this example, set the validation window size to 2.

```
options.ValidationWindowSize = 2;
```

Restrict the maximum number of generations in each tuning process to 25 so that the total number of generations in the 4-fold tuning process is the same as the previous case.

```
options.MethodOptions.MaxGenerations = 25;
```

Tune the FIS with k-fold validation.

```
if runtunefis
    % Set default random number generator.
    rng('default')

    % Tune the FIS.
    [outputFIS,optimData] = tunefis(fisin,rule,trnX,trnY,options);

    % Get the training error.
    trnErrWithKFold = optimData.tuningOutputs(end).fval

    % Calculate the test error.
    actY = evalfis(outputFIS,testX,evalOptions);
    del = actY - testY;
    testErrWithKFold = sqrt(mean(del.^2))

    % Get the function count.
    fcnCountWithKFold = optimData.totalFcnCount

    save tuningWithKFoldValidation trnErrWithKFold testErrWithKFold fcnCountWithKFold
else
    % Load the pretrained results.
    results = load('tuningWithKFoldValidation.mat');
    trnErrWithKFold = results.trnErrWithKFold
    testErrWithKFold = results.testErrWithKFold
    fcnCountWithKFold = results.fcnCountWithKFold
end


trnErrWithKFold = 2.7600

testErrWithKFold = 2.9082

fcnCountWithKFold = 5590
```

Plot the test-to-training error differences for training both with and without k-fold cases.

```
figure
cats = categorical({'Without k-fold','With k-fold'});
cats = reordercats(cats,{'Without k-fold','With k-fold'});
data = [trnErrNoKFold testErrNoKFold testErrNoKFold-trnErrNoKFold; ...
        trnErrWithKFold testErrWithKFold testErrWithKFold-trnErrWithKFold];
b = bar(cats,data);
ylabel('Root mean squared error (RMSE)')
text(b(3).XEndPoints,b(3).YEndPoints,string(b(3).YData),...
     'HorizontalAlignment','center','VerticalAlignment','bottom')
legend('Training error','Test error',...
      'Test-to-training error difference','Location','northoutside')
```

The test error performance is similar in both cases. However, the difference in the training and test errors with k-fold validation is less than without k-fold validation. Therefore, the k-fold validation reduces the bias of the training data and produces better generalized FIS parameter values. The total function count during k-fold validation is fewer than the count without k-fold validation.

```
disp(table(fcnCountNoKFold, fcnCountWithKFold, ...
    'VariableNames', ["Without k-fold" "With k-fold"], ...
    'RowName', "Function counts"))
```

	Without k-fold	With k-fold
Function counts	19210	5590

Therefore, k-fold validation reduces the number of generations in each GA optimization cycle, reducing FIS parameter overfitting. The overall k-fold validation results can be further improved by experimenting with different k-fold, tolerance, and window size values.

In general, use the following process for FIS parameter optimization with k-fold validation:

- 1 Start with a validation tolerance of 0 and a window size of 1, which provide the minimal k-fold performance.
- 2 Increase the k-fold value to achieve your desired performance. In general, use a k-fold value less than or equal to 10.
- 3 Increase the tolerance value to achieve your desired performance.

- 4 Increase the window size to achieve your desired performance.
- 5 Repeat steps 3 and 4 in a loop as necessary.

High values of tolerance, window size, and k-fold value introduce data overfitting in the optimized FIS parameter values. Therefore, use smaller values to achieve your desired tuning performance.

Local Functions

```
function [data,varName,trnX,trnY,testX,testY] = loadData

% Load the data. Each row of the dataset obtained from the repository represents
% a different automobile profile. Data contains 7 columns, where the first six
% columns contain the following input attributes.
%   - Number of cylinders
%   - Displacement
%   - Horsepower
%   - Weight
%   - Acceleration
%   - Model year
% The seventh column contains the output attribute, MPG.
[data,name] = loadGasData;

% Remove leading and trailing whitespace from the attribute names.
varName = strtrim(string(name));

% Create input and output data sets.
n = size(data,2);
x = data(:,1:n-1);
y = data(:,n);

% Create training and test data sets.
trnX = x(1:2:end,:);
trnY = y(1:2:end,:);
testX = x(2:2:end,:);
testY = y(2:2:end,:);

end

function fisin = constructFIS(data,varName)

% Create a Sugeno FIS.
fisin = sugfis;

% Add input and output variables to the FIS, where each variable represents
% one of the data attributes. For each variable, use the corresponding
% attribute name and range. To reduce the number of rules, use two MFs for
% each input variable, which results in 2^6=64 input MF combinations.
% Therefore, the FIS uses a maximum of 64 rules corresponding to the input
% MF combinations. Both input and output variables use default triangular
% MFs, which are uniformly distributed over the variable ranges.
dataRange = [min(data)' max(data)'];
numINputs = size(data,2)-1;
numInputMFs = 2;
numOutputMFs = numInputMFs^numINputs;
for i = 1:numINputs
    fisin = addInput(fisin,dataRange(i,:),...
        'Name',varName(i), 'NumMFs',numInputMFs);
end
```

```
end
```

```
% To improve data generalization, use 64 MFs for the output variable.  
% Doing so allows the FIS to use a different output MF for each rule.  
fisin = addOutput(fisin,dataRange(end,:),...  
    'Name',varName(end),'NumMFs',numOutputMFs);  
fisin.Rules = repmat(fisrule,[1 numOutputMFs]);
```

```
end
```

See Also

tunefis | tunefisOptions

More About

- “Tuning Fuzzy Inference Systems” on page 3-2

Predict Chaotic Time Series Using Type-2 FIS

This example shows chaotic time series prediction using a tuned type-2 fuzzy inference system (FIS). This example tunes the FIS using particle swarm optimization, which requires Global Optimization Toolbox™ software.

Time Series Data

This example simulates time-series data using the following form of the Mackey-Glass (MG) nonlinear delay differential equation.

$$\dot{x}(t) = \frac{0.2x(t-\tau)}{1+x^{10}(t-\tau)} - 0.1x(t)$$


Simulate the time series for 1200 samples using the following configuration.

- Sample time $t_s = 1$ sec
- Initial condition $x(0) = 1.2$
- $\tau = 20$
- $x(t-\tau) = 0$ for $t < \tau$.

```
ts = 1;
numSamples = 1200;
tau = 20;
x = zeros(1,numSamples+tau+1);
x(tau+1) = 1.2;
for t = 1+tau:numSamples+tau
    x_dot = 0.2*x(t-tau)/(1+(x(t-tau))^10)-0.1*x(t);
    x(t+1) = x(t) + ts*x_dot;
end
```

Plot the simulated MG time-series data.

```
figure(1)
plot(x(tau+2:end))
title('Mackey-Glass Chaotic Time Series')
xlabel('Time (sec)')
ylabel('x(t)')
```



Generate Training and Validation Data

Time-series prediction uses known time-series values up to time t to predict a future value at time $t + P$. The standard method for this type of prediction is to create a mapping from D sample data points, sampled every Δ units in time ($x(t - (D - 1)\Delta), \dots, x(t - \Delta), x(t)$) to a predicted future value $x = (t + P)$. For this example, set $D = 4$ and $\Delta = P = 1$. Hence, for each t , the input and output training data sets are $[x(t - 3), x(t - 2), x(t - 1), x(t)]$ and $x(t + 1)$, respectively. In other words, use four successive known time-series values to predict the next value.

Create 1000 input/output data sets from samples $x(100 + D - 1)$ to $x(1100 + D - 2)$.

```
D = 4;
inputData = zeros(1000,D);
outputData = zeros(1000,1);
for t = 100+D-1:1100+D-2
    for i = 1:D
        inputData(t-100-D+2,i) = x(t-D+i);
    end
    outputData(t-100-D+2,:) = x(t+1);
end
```

Use the first 500 data sets as training data (`trnX` and `trnY`) and the second 500 sets as validation data (`vldX` and `vldY`).

```
trnX = inputData(1:500,:);
trnY = outputData(1:500,:);
vldX = inputData(501:end,:);
vldY = outputData(501:end,:);
```

Construct FIS

This example uses a type-2 Sugeno FIS. Since a Sugeno FIS has fewer tunable parameters than a Mamdani FIS, a Sugeno system generally converges faster during optimization.

```
fisin = sugfistype2;
```

Add three inputs, each with three default triangular membership functions (MFs). Initially, eliminate the footprint of uncertainty (FOU) for each input MF by setting each lower MF equal to its corresponding upper MF. To do so, set the scale and lag values of each lower MF to 1 and 0, respectively. By eliminating the FOU for all input membership functions, you configure the type-2 FIS to behave like a type-1 FIS.


```
numInputs = D;  
numInputMFs = 3;  
range = [min(x) max(x)];  
for i = 1:numInputs  
    fisin = addInput(fisin,range,'NumMFs',numInputMFs);  
    for j = 1:numInputMFs  
        fisin.Inputs(i).MembershipFunctions(j).LowerScale = 1;  
        fisin.Inputs(i).MembershipFunctions(j).LowerLag = 0;  
    end  
end
```

For prediction, add an output to the FIS. The output contains default constant membership functions. To provide maximum resolution for the input-output mapping, set the number of output MFs equal to the number of input MF combinations.

```
numOutputMFs = numInputMFs^numInputs;  
fisin = addOutput(fisin,range,'NumMFs',numOutputMFs);
```

View the FIS structure. Initially, the FIS has zero rules. The rules of the system are found during the tuning process.

```
plotfis(fisin)
```



System fis: 4 inputs, 1 outputs, 0 rules

Tune FIS with Training Data

To tune the FIS, you use the following three steps.

- 1 Learn the rule base while keeping the input and output MF parameters constant.
- 2 Tune the output MF parameters and the upper MF parameters of the inputs while keeping the rule and lower MF parameters constant.
- 3 Tune the lower MF parameters of the inputs while keeping the rule, output MF, and upper MF parameters constant.

The first step is less computationally expensive due to the small number of rule parameters, and it quickly converges to a fuzzy rule base during training. After the second step, the system is a trained type-1 FIS. The third step produces a tuned type-2 FIS.

Learn Rules

To learn a rule base, first specify tuning options using a `tunefisOptions` object.

```
options = tunefisOptions;
```

Since the FIS does not contain any pretuned fuzzy rules, use a global optimization method (genetic algorithm or particle swarm) to learn the rules. Global optimization methods perform better in large parameter tuning ranges as compared to local optimization methods (pattern search and simulated annealing). For this example, tune the FIS using particle swarm optimization ('particleswarm').

```
options.Method = 'particleswarm';
```

To learn new rules, set the `OptimizationType` to `'learning'`.

```
options.OptimizationType = 'learning';
```

Restrict the maximum number of rules to the number of input MF combinations. The number of tuned rules can be less than this limit, since the tuning process removes duplicate rules.

```
options.NumMaxRules = numInputMFs^numInputs;
```

If you have Parallel Computing Toolbox™ software, you can improve the speed of the tuning process by setting `UseParallel` to `true`. If you do not have Parallel Computing Toolbox software, set `UseParallel` to `false`.

```
options.UseParallel = false;
```

Set the maximum number of iterations to 10. Increasing the number of iterations can reduce training error. However, the larger number of iterations increases the duration of the tuning process and can overtune the rule parameters to the training data.

```
options.MethodOptions.MaxIterations = 10;
```

Since particle swarm optimization uses random search, to obtain reproducible results, initialize the random number generator to its default configuration.

```
rng('default')
```

Tuning a FIS using the `tunefis` function takes several minutes. For this example, enable tuning by setting `runtunefis` to `true`. To load pretrained results without running `tunefis`, you can set `runtunefis` to `false`.


```
runtunefis = false;
```

Tune the FIS using the specified training data and options.

```
if runtunefis
    fisout1 = tunefis(fisin,[],trnX,trnY,options);
else
    tunedfis = load('tunedfischaotictimeseriestype2.mat');
    fisout1 = tunedfis.fisout1;
end
```

View the structure of the trained FIS, which contains the new learned rules.


```
plotfis(fisout1)
```

System fis: 4 inputs, 1 outputs, 69 rules


Check the individual input-output relationships tuned by the learned rule base. For example, the following figure shows the relationship between the second input and the output.

```
gensurf(fisout1,gensurfOptions('InputIndex',2))
```



Evaluate the tuned FIS using the input validation data. Plot the actual generated output with the expected validation output, and compute the root-mean-square-error (RMSE).

```
plotActualAndExpectedResultsWithRMSE(fisout1,vldX,vldY)
```



Tune Upper Membership Function Parameters

Tune the upper membership function parameters. A type-2 Sugeno FIS supports only crisp output functions. Therefore, this step tunes input upper MFs and crisp output functions.

Obtain the input and output parameter settings using `getTunableSettings`. Since the FIS uses triangular input MFs, you can tune the input MFs using asymmetric lag values.

```
[in,out] = getTunableSettings(fisout1,'AsymmetricLag',true);
```

Disable the tuning of lower MF parameters.

```
for i = 1:length(in)
    for j = 1:length(in(i).MembershipFunctions)
        in(i).MembershipFunctions(j).LowerScale.Free = false;
        in(i).MembershipFunctions(j).LowerLag.Free = false;
    end
end
```

To optimize the existing tunable MF parameters while keeping the rule base constant, set `OptimizationType` to 'tuning'.

```
options.OptimizationType = 'tuning';
```

Tune the FIS using the specified tuning data and options. To load pretrained results without running `tunefis`, you can set `runtunefis` to `false`.

```
rng('default')
if runtunefis
```


```

    fisout2 = tunefis(fisout1,[in;out],trnX,trnY,options);
else
    tunedfis = load('tunedfischaotictimeseriestype2.mat');
    fisout2 = tunedfis.fisout2;
end

```

View the structure of the trained FIS, which now contains tuned upper MF parameters.


```
plotfis(fisout2)
```



System fis: 4 inputs, 1 outputs, 69 rules

Evaluate the tuned FIS using the validation data, compute the RMSE, and plot the actual generated output with the expected validation output.

```
plotActualAndExpectedResultsWithRMSE(fisout2,vldX,vldY)
```



Tuning the upper MF parameters improves the performance of the FIS. This result is equivalent to tuning a type-1 FIS.

Tune Lower Membership Function Parameters

Tune only the input lower MF parameters. To do so, set the lower scale and lag values tunable, and disable tuning of the upper MF parameters.


```
for i = 1:length(in)
    for j = 1:length(in(i).MembershipFunctions)
        in(i).MembershipFunctions(j).UpperParameters.Free = false;
        in(i).MembershipFunctions(j).LowerScale.Free = true;
        in(i).MembershipFunctions(j).LowerLag.Free = true;
    end
end
```

Tune the FIS using the specified tuning data and options. To load pretrained results without running `tunefis`, you can set `runtunefis` to `false`.

```
rng('default')
if runtunefis
    fisout3 = tunefis(fisout2,in,trnX,trnY,options);
else
    tunedfis = load('tunedfischaotictimeserietype2.mat');
    fisout3 = tunedfis.fisout3;
end
```

View structure of the trained FIS, which now contains tuned lower MF parameters.


```
plotfis(fisout3)
```



System fis: 4 inputs, 1 outputs, 69 rules

Evaluate the tuned FIS using the validation data, compute the RMSE, and plot the actual generated output with the expected validation output.

```
plotActualAndExpectedResultsWithRMSE(fisout3,vldX,vldY)
```



Tuning both the upper and lower MF values improves the FIS performance. The RMSE improves when the trained FIS includes both tuned upper and lower parameter values.

Conclusion

Type-2 MFs provides additional tunable parameters as compared to type-1 MFs. Therefore, with adequate training data, a tuned type-2 FIS can fit the training data better than a tuned type-1 FIS.

Overall, you can produce different tuning results by modifying any of the following FIS properties or tuning options:

- Number of inputs
- Number of MFs
- Type of MFs
- Optimization method
- Number of tuning iterations

Local Functions

```
function [rmse,actY] = calculateRMSE(fis,x,y)

% Specify options for FIS evaluation
evalOptions = evalfisOptions("EmptyOutputFuzzySetMessage","none", ...
    "NoRuleFiredMessage","none","OutOfRangeInputValueMessage","none");
```

```
% Evaluate FIS
actY = evalfis(fis,x,evalOptions);

% Calculate RMSE
del = actY - y;
rmse = sqrt(mean(del.^2));

end

function plotActualAndExpectedResultsWithRMSE(fis,vldX,vldY)
[rmse,actY] = calculateRMSE(fis,vldX,vldY);

figure
plot([actY vldY])
axis([0 length(vldY) min(vldY)-0.01 max(vldY)+0.13])
xlabel('sample index')
ylabel('signal value')
title(['RMSE = ' num2str(rmse)])
legend(["Actual output" "Expected output"],'Location','northeast')
end
```

See Also

tunefis | sugfistype2

More About


- “Type-2 Fuzzy Inference Systems” on page 2-7
- “Tuning Fuzzy Inference Systems” on page 3-2

Tune Fuzzy Robot Obstacle Avoidance System Using Custom Cost Function

This example shows how to tune a fuzzy inference system (FIS) using a custom cost function. The example requires Global Optimization Toolbox™ software.

Problem Description

In this example, you use a custom cost function to learn robot navigation in a simulation environment. The goal of the navigation task is to reach a specified target while avoiding obstacles. The direction to the target is represented as a unit force vector (\vec{F}_t) directed from the robot to a target location. The obstacle avoidance direction is represented by a unit force vector (\vec{F}_o) directed towards the robot from the closest obstacle location.



The robot, target, and obstacle are shown as circles with 0.5 m radius in the 25 m x 25 m simulation environment. The navigation task is to combine the force vectors such that the direction θ of the resultant force vector \vec{F} provides a collision-free direction for the robot.

$$\vec{F} = w\vec{F}_o + (1 - w)\vec{F}_t, \text{ where } 0 \leq w \leq 1$$

$$\theta = \angle \vec{F}$$

This example assumes a robot with differential kinematics for the simulation. In other words, the robot can rotate on its center without any constraints. However, to avoid sharp turns, the change per

time step in the robot direction is limited to $[-\frac{\pi}{4}, \frac{\pi}{4}]$. Therefore, if the current robot heading direction is $\theta_r(k)$, the next heading direction is calculated as:

$$\theta_r(k + 1) = \theta_r(k) + \min\left(\max\left(\theta - \theta_r(k), \frac{\pi}{4}\right), -\frac{\pi}{4}\right).$$

The weight w of the force vector \vec{F}_o is calculated using function f_w :

$$w = f_w(\alpha, \theta_{t,o})$$

where

- $\alpha = \frac{d_o}{d_t}$ is the ratio of the robot-to-obstacle distance (d_o) and the robot-to-target-distance (d_t)
- $\theta_{t,o}$ is the absolute difference between the target and obstacle directions with respect to the robot

To achieve the navigation task, the function f_w must generate high w values, that is, focus on avoiding the obstacle when:

- Both the target and obstacle directions from the robot are similar ($\theta_{t,o}$ is low)
- The obstacle is closer to the robot than the target (α is low).

Otherwise, f_w must generate low w values, that is, focus on reaching the target.

The goal of this example is to design a FIS that learns fuzzy rules and optimizes the FIS parameters to model the function f_w for collision-free robot navigation in the simulation environment.


Assumptions

The following assumptions apply for the robot simulation:

- The robot can perfectly localize in the simulation environment; that is, the robot knows its current position in the simulation environment.
- The robot is equipped with perfect sensors to identify the obstacle and determine its location.
- The robot has no dynamic constraints; that is, the robot can rotate and move as commanded without any mechanical constraints. To avoid sharp turns, a soft constraint is imposed on rotation, which limits the change per time step in the robot heading to $[-\frac{\pi}{4}, \frac{\pi}{4}]$.
- The robot runs with a fixed speed. You can include additional fuzzy systems to control the robot speed. For simplicity, this example uses a fixed speed for the robot.

Construct Fuzzy System

To model function f_w , construct a FIS as shown in the following figure. For this example, use a Mamdani FIS.



```
fisin = mamfis;
```

Add the following two inputs as shown in the previous figure.

- α — Ratio of distances, robot-to-obstacle / robot-to-target
- $\theta_{t,o}$ — Difference between target and obstacle directions

Set the range of the first input to $[0, 2]$, which indicates that α contributes to obstacle avoidance when the obstacle distance is less than or equal to twice the target distance.

Set the range of the second input to $[0, \pi/2]$, which indicates that $\theta_{t,o}$ contributes to obstacle avoidance when the difference between the target and obstacle directions is less than or equal to $\pi/2$.

```
fisin = addInput(fisin,[0 2], 'Name', 'alpha');
fisin = addInput(fisin,[0 pi/2], 'Name', 'theta_t_o');
```

To minimize the number of rules, which corresponds to the number of combinations of input membership functions, add two membership functions (MFs) to each input. To generate similar membership values beyond the input ranges, use zmf (Z-shaped curve membership function) and smf (S-shaped curve membership function) MFs. The tuning process optimizes the input MF parameter values.

Add membership functions to the first input.

```
fisin = addMF(fisin, 'alpha', 'zmf', [0 2], 'Name', 'low');
fisin = addMF(fisin, 'alpha', 'smf', [0 2], 'Name', 'high');
```

Add membership functions to the second input.

```
fisin = addMF(fisin, 'theta_t_o', 'zmf', [0 pi/2], 'Name', 'low');
fisin = addMF(fisin, 'theta_t_o', 'smf', [0 pi/2], 'Name', 'high');
```

Add an output to the FIS or the obstacle force vector weight, restricting the weight values to the range $[0, 1]$.


```
fisin = addOutput(fisin,[0 1], 'Name', 'w');
```

Add two MFs to the output. You can add more MFs to the output for finer granularity of output values. However, doing so increases the number of tuning parameters. The output MFs also use zmf and smf to generate similar membership values beyond the input ranges. The tuning process optimizes the output MF parameter values.

```
fisin = addMF(fisin, 'w', 'zmf', [0 1], 'Name', 'low');
fisin = addMF(fisin, 'w', 'smf', [0 1], 'Name', 'high');
```

View the FIS structure. Initially, the FIS has zero rules. The tuning process finds rules for the fuzzy system.

```
figure
plotfis(fisin)
```



System fis: 2 inputs, 1 outputs, 0 rules

Learn Rules and Optimize FIS Parameters

Since you do not have training data for this example, you simulate the robot navigation using a custom cost function. The tuning process uses this custom cost function when optimizing the FIS parameters.

For parameter optimization, obtain the parameter settings from the FIS.

```
[in,out] = getTunableSettings(fisin);
```

Next, create tuning options with `OptimizationType` set to `learning`. This example uses the genetic algorithm (ga) optimization method for the tuning process. To improve the speed of the tuning process, set the `UseParallel` option to `true`, which requires Parallel Computing Toolbox™ software. If you do not have Parallel Computing Toolbox software, set `UseParallel` to `false`.

```
options = tunefisOptions('Method','ga','OptimizationType','learning');
```

Set the population size of the genetic algorithm to 200. The larger population size increases the probability of generating a better solution in fewer generations.

```
options.MethodOptions.PopulationSize = 200;
```


Set the maximum number of generations to 25. To tune the parameters further, you can set a higher number of generations. However, doing so increases the duration of the tuning process and can overtune the parameter values.

```
options.MethodOptions.MaxGenerations = 25;
```

Set the locations of the obstacle, target, and robot for the training environments. Set the initial heading of the robot to $\pi/2$ for the training environment. To learn navigation both with and without obstacle avoidance on the way to the target location, use two training tasks with different obstacle locations.

```
trnObstacle = [3 12;13 18];
trnTarget = [13 22;13 22];
trnRobot = [13 2 pi/2;13 2 pi/2;];
```

```
showSimulationEnvironmentsForTraining(trnObstacle, trnTarget, trnRobot)
```



Specify the custom cost function using a function handle.

```
costFunction = @(fis)navigationCostFcn(fis, trnObstacle, trnTarget, trnRobot);
```

In the cost function, the robot navigation is simulated in the training environments using each FIS from the population. Each navigation task is run for 100 iterations, where each iteration is equivalent to a decision cycle of length 1 s. The robot uses a fixed speed of 0.5 m/s throughout the navigation task. For more simulation details, see the `getNavigationResults` function.

```
function cost = navigationCostFcn(fis, obstacle, target, robot)
cost = 0;
for i = 1:size(obstacle,1)
results = getNavigationResults(fis, obstacle(i,:), target(i,:), robot(i,:));
cost = cost + getNavigationCost(results);
end
end
```

The cost of each navigation task is the total distance traveled by the robot. If the robot does not reach the target or collides with the obstacle, a high cost value (200) is assigned for the simulation.

```
function cost = getNavigationCost(results)
if results.notSafe || ~results.reachedTarget
cost = 200;
else
```

```

cost = results.travelledDistance;
end
end

```

Since genetic algorithm optimization uses random search, to obtain reproducible results, initialize the random number generator to its default configuration.

```
rng('default')
```

Learning rules using the `tunefis` function takes approximately 10 minutes. For this example, enable tuning by setting `runtunefis` to `true`. To load pretrained results without running `tunefis`, you can set `runtunefis` to `false`.

```
runtunefis = false;
```

Tune the FIS using the specified training environments and tuning options.


```

if runtunefis
    fisout = tunefis(fisin,[in;out],costFunction,options); %#ok<UNRCH>
else
    tunedfis = load('tunedfisnavigation.mat');
    fisout = tunedfis.fisout;
end

```

The tuned FIS produces the following robot trajectories in the simulation environments.


```
showNavigationTrajectories(fisout,trnObstacle,trnTarget,trnRobot)
```



In the first case, the robot reaches the target with minimum distance since the obstacle is not on the path to the target. In the second case, the robot successfully avoids the obstacle and reaches the target.

View the structure of the tuned FIS, `fisout`.

```
figure
plotfis(fisout)
```



System fis: 2 inputs, 1 outputs, 5 rules

The tuning process produces a set of new rules for the FIS.

```
fisout.Rules
```

```
ans =
  1x5 fisrule array with properties:
```

```
  Description
  Antecedent
  Consequent
  Weight
  Connection
```

```
Details:
```

```
      Description
```

```
-----
 1  "alpha==low & theta_t_o==high => w=low (1)"
 2  "alpha==low & theta_t_o==low => w=high (1)"
 3  "theta_t_o==high => w=low (1)"
 4  "alpha==high & theta_t_o==high => w=low (1)"
 5  "alpha==low => w=low (1)"
```

The rules are described as follows with respect to the expected behaviors of f_w :

- Rule 1 is consistent with the expected behavior of f_w . When the obstacle is not located in front of the robot on the way to the target ($\theta_{t,o}$ is high) and the obstacle is close (α is low), this rule produces low weight values.
- Rule 4 is also consistent with the expected behavior of f_w . When the obstacle is not located in front of the robot on the way to the target ($\theta_{t,o}$ is high) and the obstacle is farther away (α is high), this rule produces low weight values.
- Rule 3 generates low weight values when the obstacle is not located in front of the robot ($\theta_{t,o}$ is high), irrespective of the obstacle distance. This rule covers the conditions for both rule 1 and rule 4. Therefore, rules 1 and 4 are redundant and can be removed.
- Rule 2 is also consistent with the expected behavior of f_w . When the obstacle is close to the robot (α is low) and is located in front of the robot on the way to the target ($\theta_{t,o}$ is low), this rule produces high weight values for the obstacle avoidance task.
- Rule 5 generates low weight values when the obstacle distance is low. This rule contradicts rule 2 when $\theta_{t,o}$ is low. In this case, the output of rule 5 does not contribute to the final output due to the high output values of rule 2. Therefore, rule 5 can also be removed.

Remove the redundant rules.

```

fisoutpruned = fisout;
fisoutpruned.Rules([1 4 5]) = [];
fisoutpruned.Rules

ans =
    1x2 fisrule array with properties:

    Description
    Antecedent
    Consequent
    Weight
    Connection

Details:
           Description
-----
1    "alpha==low & theta_t_o==low => w=high (1)"
2    "theta_t_o==high => w=low (1)"


```

`fisout` and `fisoutpruned` generate similar control surfaces. Therefore, only two rules are necessary for obstacle avoidance in the simulation environment.

```

figure
subplot(1,2,1)
gensurf(fisout)
title('Output surface of fisout')
subplot(1,2,2)
gensurf(fisoutpruned)
title('Output surface of fisoutpruned')

```





Check Performance

Validate the performance of the tuned FIS with different positions of the obstacle, robot, and target. In the following validation cases, the robot successfully avoids the obstacle to reach the target position using the tuned FIS.

```
vldObstacle = [13 5;10 10;8 8];
vldRobot = [5 12 0;5 20 -pi/2;19 19 -pi];
vldTarget = [23 12;15 4;5 5];
```

```
showNavigationTrajectories(fisoutpruned,vldObstacle,vldTarget,vldRobot)
```



Conclusion

This example uses a custom cost function that simulates robot navigation in different training environments to learn fuzzy rules and optimize the FIS parameter values for collision-free navigation. You can include more training environments to learn obstacle avoidance in other scenarios, for example narrow corridor and U-shape obstacles. In these scenarios, the robot may need additional navigation subtasks, such as wall following and subtarget (intermediate landmark) reaching, for successful collision-free navigation to the target. Complex environments also require additional terms in the cost calculation for safe navigation. For example, in a narrow corridor the robot should stay in the middle; that is, the distances to the obstacles on the left and right should be the same.

Using a custom cost function with `tunefis` provides the flexibility of simulating a custom system with custom cost calculation. However, the tradeoff is a lengthy tuning process due to the number of simulations required (for each set of optimized parameter values). Therefore, if possible, to expedite the tuning process, use training data. For instance, the tuning process in this example would run faster if input/output decision data of a human operator was available for tuning the FIS.

Local Functions

```
function showSimulationEnvironment(obstacle,target,robot,navigationResults)

% Show the robot trajectory in the simulation environment.

% Radius of the robot, target, and obstacle.
radius = 1; % 1m

% Use 25mx25m simulation environment.
axis([0 25 0 25]);

% Set equal aspect ratio.
pbaspect([1 1 1])

% Temporary plots to enable legends.
hold on
plot(robot(1),robot(2)+radius,'ob','LineWidth',radius*1,'MarkerFaceColor','b')
plot(robot(1),robot(2)+radius,'or','LineWidth',radius*1,'MarkerFaceColor','r')
plot(robot(1),robot(2)+radius,'og','LineWidth',radius*1,'MarkerFaceColor','g')
hold off

% Draw obstacle.
rectangle('Position',[obstacle(1)-0.5*radius obstacle(2)+0.5*radius radius radius], ...
    'Curvature',[1 1],'FaceColor','b','EdgeColor','b')

% Draw target.
rectangle('Position',[target(1)-0.5*radius target(2)+0.5*radius radius radius], ...
    'Curvature',[1 1],'FaceColor','r','EdgeColor','r')

% Draw robot.
rectangle('Position',[robot(1)-0.5*radius robot(2)+0.5*radius radius radius], ...
    'Curvature',[1 1],'FaceColor','g','EdgeColor','g')

% Add labels, title, and legends.
xlabel('x (m)'),ylabel('y (m)')
title('Simulation Environment for Robot Navigation')
legend(["Obstacle" "Target" "Robot"])

% Plot the robot trajectory if specified.
```

```

if nargin == 4
    x = navigationResults.x;
    y = navigationResults.y;
    for i = 1:numel(x)
        rectangle('Position',[x(i)-0.5*radius y(i)+0.5*radius radius radius], ...
            'Curvature',[1 1], 'FaceColor','g', 'EdgeColor','g')
    end
end

end

function showSimulationEnvironmentsForTraining(obstacle,target,robot)

% Show simulation environments for training.
drawEnvironmentAndShowTrajectory(obstacle,target,robot, 'Training Task')

end

function showNavigationTrajectories(fis,obstacle,target,robot)

% Show robot trajectories in the simulation environments.
drawEnvironmentAndShowTrajectory(obstacle,target,robot, 'Navigation Task',fis)

end

function drawEnvironmentAndShowTrajectory(obstacle,target,robot,plotTitle,varargin)

% Expand figure horizontally to tile the simulation environments.
h = figure;
h.Position = [h.Position(1:2) 3*h.Position(3) h.Position(4)];
numTasks = size(target,1);

% Draw each simulation environment.
for i = 1:numTasks
    o = obstacle(i,:);
    t = target(i,:);
    r = robot(i,:);
    subplot(1,numTasks,i)
    if ~isempty(varargin)
        results = getNavigationResults(varargin{1},o,t,r);
        showSimulationEnvironment(o,t,r,results)
    else
        showSimulationEnvironment(o,t,r)
    end
    end
    title([plotTitle ': ' num2str(i)])
end

end

```

See Also

tunefis | mamfis | getTunableSettings

More About

- “Tuning Fuzzy Inference Systems” on page 3-2
- “Tune Mamdani Fuzzy Inference System” on page 3-28

Classify Pixels Using Fuzzy Systems

This example shows how to classify image pixels using a fuzzy inference system (FIS). This example requires Image Processing Toolbox™ software.

Pixel classification is an image processing technique that segments an image by classifying each pixel according to specific pixel attributes. Noise and other sources of uncertainty can complicate pixel classification. Using a FIS-based method for classification can help address such uncertainty.

This example includes the following stages.

- 1 Tune a FIS to classify pixels based on color.
- 2 Tune a FIS to classify pixels based on texture.
- 3 Combine the tuned FIS objects into a hierarchical fuzzy system for pixel classification.

Load the image data, which contains three visible segments: green grass, white border, and soccer ball.

```
exData = load('fuzzpixclass');  
cImg = exData.cImg;
```

```
figure  
imshow(cImg)
```



This example uses fuzzy systems to segment the image into three categories by classifying each pixel as belonging to the green grass, white border, or soccer ball.

Segment Image Using Color

The image segments include the following color attributes.


- Green field: variation of green and dark shadow pixels
- White border: white, light green, and dark shadow pixels
- Soccer ball: white and dark color pixels

Since the number of dark pixels is insignificant compared to the green and white pixels, you can create one fuzzy classifier to distinguish between green and white pixels. You can train the classifiers with sample green and white pixels since none of the segments include unique color attribute.

Extract representative subimages from the green field and white border segments as training data. Each subimage includes variations in pixel color.

```
grnImg = exData.grnImg;
whtImg = exData.whtImg;

figure
subplot(1,2,1)
imshow(grnImg)
xlabel('Green subimage')
subplot(1,2,2)
imshow(whtImg)
xlabel('White subimage')
```



Green subimage



White subimage

Construct FIS

For color segmentation, construct a three-input, one-output Sugeno FIS without rules. For each input and output variable, include two default membership functions (MFs).

```
colorFISIn = sugfis('NumInputs',3,'NumInputMFs',2, ...
    'NumOutputs',1,'NumOutputMFs',2,'AddRules','none');
```

The input variables correspond to the RGB values for each pixel. The output value is high if the pixel color is green; otherwise it is low.

Train FIS

Create training data from the representative color subimages. The `getColorInputData` helper function, which is shown at the end of the example, creates a three-column array of RGB values for each pixel in a specified image.

```
[grnSubRow,grnSubCol,grnSubDepth] = size(grnImg); % Green subimage size
[whtSubRow,whtSubCol,whtSubDepth] = size(whtImg); % White subimage size
trnX = [...
    getColorInputData(grnImg); ...
    getColorInputData(whtImg) ...
    ];
trnY = [...
    ones(grnSubRow*grnSubCol,1); ... % Output is high (1) for green pixels
    zeros(whtSubRow*whtSubCol,1) ... % Output is low (1) for white pixels
    ];
```

Input data `trnX` has three columns for the RGB pixel values. Output data `trnY` is a column vector that contains a 1 for each green pixel and a 0 for each white pixel.

Create an option set for learning rules for `colorFISIn`. To reduce the duration of the optimization process, use the minimum values for cross-validation parameters.

```
options = tunefisOptions('OptimizationType','learning','KFoldValue',2, ...
    'ValidationTolerance',0.0,'ValidationWindowSize',1);
```

If you have Parallel Computing Toolbox™ software, you can improve the speed of the tuning process by setting `options.UseParallel` to `true`. If you do not have Parallel Computing Toolbox software, set `options.UseParallel` to `false`.

To learn rules and find FIS parameter values, this example uses genetic algorithm optimization, which is a stochastic process. To obtain reproducible results, initialize the random number generator to its default configuration.

```
rng('default')
```

Learn fuzzy rules for `colorFISIn` using the training data and options. Learning rules using the `tunefis` function can take several minutes. For this example, you can enable tuning by setting `runtunefis` to `true`. To load pretrained results without running `tunefis`, set `runtunefis` to `false`.

```
runtunefis = false;
```

To learn new rules without tuning input and output MF parameters, set the parameter settings to `[]`. For more information, see `tunefis`.

```
if runtunefis
    colorFISOut1 = tunefis(colorFISIn,[],trnX,trnY,options); %#ok<UNRCH>
else
    colorFISOut1 = exData.colorFISOut1;
end
```

Calculate the root mean squared error (RMSE) for the trained FIS. The `calculateRMSE` helper function, which is shown at the end of the example, classifies the training data pixels using the trained FIS and compares the results to the expected pixel classifications.

```
fprintf('Training RMSE after learning rules = %.3f MPG\n',...
    calculateRMSE(colorFISOut1,trnX,trnY));
```

```
Training RMSE after learning rules = 0.283 MPG
```

After learning the new rules, tune the input and output MF parameters. To obtain the tunable parameter settings of the FIS, use the `getTunableSettings` function.

```
[in,out] = getTunableSettings(colorFISOut1);
```

To tune the existing FIS parameter values without learning new rules, set the `OptimizationType` to `'tuning'`.

```
options.OptimizationType = 'tuning';
```

Tune the FIS parameters using the specified tunable settings, training data, and tuning options.

```
if runtunefis
    rng('default')
    colorFISOut = tunefis(colorFISOut1,[in;out],trnX,trnY,options);
    colorFISOut.Name = "colorFISOut";
else
    colorFISOut = exData.colorFISOut;
```

```
end
```

Calculate the RMSE for the tuned FIS.

```
fprintf('Training RMSE after tuning MF parameters = %.3f MPG\n',...
    calculateRMSE(colorFISOut,trnX,trnY));
```

```
Training RMSE after tuning MF parameters = 0.228 MPG
```

Segment Image

Segment the original image using the tuned FIS. To do so, first extract the red, green, and blue pixel values.

```
[imgRow,imgCol,imgDepth] = size(cImg);
red = cImg(:,:,1);
green = cImg(:,:,2);
blue = cImg(:,:,3);
colorInput = [red(:) green(:) blue(:)];
```

Classify each pixel using the tuned FIS.

```
eoptions = evalfisOptions;
eoptions.EmptyOutputFuzzySetMessage = 'none';
eoptions.NoRuleFiredMessage = 'none';
eoptions.OutOfRangeInputValueMessage = 'none';
```

```
y = evalfis(colorFISOut,colorInput,eoptions);
```

Segment the image using the `getSegmentedImage` helper function, which is shown at the end of the example. This function creates a binary mask from the FIS output values.

```
greenSegment = getSegmentedImage(reshape(y,[imgRow,imgCol]),cImg);
```

View the segmented image. Pixels that the FIS classified as white are shown in black. The remaining pixels are classified as green.

```
figure  
imshow(greenSegment)
```



White pixels are partially removed from the border and ball segments. The green segment also incorrectly includes pixels from the ball. Therefore, the classification process requires another pixel attribute that can identify the difference between the grass field and the ball.

Segment Image Using Texture

To distinguish between the field and the ball, use gray image gradient data to identify textures of the field and the ball.

Extract a representative subimage for the ball, and convert the green, white, and ball subimages to grayscale.

```
ballImg = exData.ballImg;  
grayGrnImg = rgb2gray(grnImg);  
grayWhtImg = rgb2gray(whtImg);  
grayBallImg = rgb2gray(ballImg);
```

Compute the gradient for each subimage and normalize the gradient magnitude for each pixel using the `normMat` helper function.

```
[gX,gY] = imgradientxy(grayGrnImg);  
grnGrSTexture = normMat(imgradient(gX,gY));
```




```
[gX,gY] = imgradientxy(grayWhtImg);
whtGrGrTexture = normMat(imgradient(gX,gY));
```

```
[gX,gY] = imgradientxy(grayBallImg);
ballTexture = normMat(imgradient(gX,gY));
```

View the gradients for each subimage.

```
figure,
subplot(2,3,1)
imshow(grnImg)
subplot(2,3,2)
imshow(whtImg)
subplot(2,3,3)
imshow(ballImg)
subplot(2,3,4)
imshow(grnGrGrTexture)
subplot(2,3,5)
imshow(whtGrGrTexture)
subplot(2,3,6)
imshow(ballTexture)
```



Both the green and white grass segments have similar gradient values, which are different than those of the ball segment. Therefore, use only the green and ball segment gradient data to train a fuzzy texture classifier.

Construct FIS

The normalized gradients for the ball and grass field have different patterns. To learn these patterns, create a three-input, one-output Sugeno FIS without rules. For each input and output variable, include two default membership functions (MFs).

```
textureFISIn = sugfis('NumInputs',3,'NumInputMFs',2, ...
    'NumOutputs',1,'NumOutputMFs',2,'AddRules','none');
```

The input variables specify gradient values for three successive pixels. The output value is high if the third pixel belongs to the grass field; otherwise, it is low.

Train FIS

Create training data from the gradients of the green and ball regions. The `getGradientInputData` helper function, which is shown at the end of the example, creates a three-column array of successive pixel value combinations.

```
[grsGradRow,grsGradCol] = size(grnGrsTexture); % Grass texture size
[ballGradRow,ballGradCol] = size(ballTexture); % Ball texture size
trnX = [...
    getGradientInputData(grnGrsTexture); ... % gradient values of 3 successive pixels
    getGradientInputData(ballTexture) ... % gradient values of 3 successive pixels
];
trnY = [...
    ones(grsGradRow*grsGradCol,1); ... % Output is high (1) for green texture
    zeros(ballGradRow*ballGradCol,1) ... % Output is low (1) for ball texture
];
```

Input data `trnX` has three columns for the gradient values of the three successive pixels. Output data `trnY` is a column vector that contains a 1 if the third pixel belongs to field texture and a 0 otherwise.

To learn fuzzy rules, set the `OptimizationType` to `'learning'`.

```
options.OptimizationType = 'learning';
```

Train `textureFISIn` to learn rules using the training data.

```
if runtunefis
    rng('default')
    textureFISOut1 = tunefis(textureFISIn,[],trnX,trnY,options); %#ok<UNRCH>
else
    textureFISOut1 = exData.textureFISOut1;
end
fprintf('Training RMSE after learning rules = %.3f MPG\n',...
    calculateRMSE(textureFISOut1,trnX,trnY));
```

```
Training RMSE after learning rules = 0.477 MPG
```

After learning the new rules, tune the input and output MF parameters. To obtain the tunable parameters of the FIS, use the `getTunableSettings` function.

```
[in,out] = getTunableSettings(textureFISOut1);
```

To tune the existing FIS parameters without learning new rules, set the `OptimizationType` to `'tuning'`.

```
options.OptimizationType = 'tuning';
```

Tune the FIS parameters using the specified tunable settings, training data, and tuning options.

```
if runtunefis
    rng('default')
    textureFISOut = tunefis(textureFISOut1,[in;out],trnX,trnY,options);
    textureFISOut.Name = "textureFISOut";
else
    textureFISOut = exData.textureFISOut;
end
fprintf('Training RMSE after tuning MF parameters = %.3f MPG\n',...
    calculateRMSE(textureFISOut,trnX,trnY));
```

Training RMSE after tuning MF parameters = 0.442 MPG

Segment Image

Segment the original image using the tuned FIS. To do so, first compute the image gradient and extract the successive pixel combinations.

```
[gX,gY] = imgradientxy(rgb2gray(cImg));
imgTexture = normMat(imgradient(gX,gY));
gradInput = getGradientInputData(imgTexture);
```

Classify each pixel using the tuned FIS.

```
y = evalfis(textureFISOut,gradInput,eoptions);
```

Segment the image using the `getSegmentedImage` helper function.

```
grassField = getSegmentedImage(reshape(y,[imgRow,imgCol]),cImg);
```

View the segmented image. Pixels that the FIS classified as belonging to the ball are shown in black. The remaining pixels are classified as field pixels.

```
figure
imshow(grassField)
```



The trained FIS segments the grass field and the ball with few incorrect pixels in the segments.

Segment Image Using Both Color and Texture

To classify pixels based on both color and texture, you can combine `colorFISOut` and `textureFISOut` using a hierarchical fuzzy system, or FIS tree.

To do so, first create a Sugeno FIS with two inputs and three outputs. The first input variable is the output of `colorFISOut` and the second input variable is the output of `textureFISOut`. The output variables are the degree to which a pixels belongs to each image segment: green field, white border, and soccer ball.

```
segFIS = sugfis('Name','segFIS','NumInputs',2,'NumInputMFs',2, ...  
              'NumOutputs',3,'NumOutputMFs',2,'AddRules','none');
```

Name the input variables, output variable, and MFs.

```
segFIS.Inputs(1).Name = 'color';  
segFIS.Inputs(1).MembershipFunctions(1).Name = 'white';  
segFIS.Inputs(1).MembershipFunctions(2).Name = 'green';  
segFIS.Inputs(2).Name = 'texture';  
segFIS.Inputs(2).MembershipFunctions(1).Name = 'ball';  
segFIS.Inputs(2).MembershipFunctions(2).Name = 'grass';  
segFIS.Outputs(1).Name = 'greenField';  
segFIS.Outputs(1).MembershipFunctions(1).Name = 'low';  
segFIS.Outputs(1).MembershipFunctions(2).Name = 'high';  
segFIS.Outputs(2).Name = 'whiteBorder';  
segFIS.Outputs(2).MembershipFunctions(1).Name = 'low';  
segFIS.Outputs(2).MembershipFunctions(2).Name = 'high';  
segFIS.Outputs(3).Name = 'soccerBall';
```

```
segFIS.Outputs(3).MembershipFunctions(1).Name = 'low';
segFIS.Outputs(3).MembershipFunctions(2).Name = 'high';
```

Add the following rules to the FIS.

- If the pixel has a smooth ball texture, set the soccer ball output to high.
- If the pixel is white and has a grass texture set the white border output to high.
- If the pixel is green and has a grass texture and is green field output to high.

```
rules = ["texture==ball => greenField=low, whiteBorder=low, soccerBall=high";
        "color==white & texture==grass => greenField=low, whiteBorder=high, soccerBall=low";
        "color==green & texture==grass => greenField=high, whiteBorder=low, soccerBall=low"];
segFIS = addRule(segFIS, rules);
```

Create a FIS tree by connecting the outputs of colorFIS0out and textureFIS0out to the inputs of segFIS.

```
fis = [colorFIS0out textureFIS0out segFIS];
con = [...
        "colorFIS0out/output1" "segFIS/color"; ...
        "textureFIS0out/output1" "segFIS/texture" ...
    ];
fisT = fistree(fis, con);
```

Classify the image pixels using the FIS tree and segment the image. For each segmented image, the nonblack pixels are classified as part of the segment.

```
y = evalfis(fisT, [colorInput gradInput], eoptions);
greenField = getSegmentedImage(reshape(y(:,1), [imgRow, imgCol]), cImg);
whiteBorder = getSegmentedImage(reshape(y(:,2), [imgRow, imgCol]), cImg);
soccerBall = getSegmentedImage(reshape(y(:,3), [imgRow, imgCol]), cImg);
```

View the green field pixels.

```
figure
imshow(greenField)
xlabel('Green field')
```



Green field

View the white border pixels.

```
figure
imshow(whiteBorder)
xlabel('White border')
```



White border

View the soccer ball pixels.

```
figure  
imshow(soccerBall)  
xlabel('Soccer ball')
```



Soccer ball

Conclusion

The image segments contain incorrect classifications. You can remove many of the misclassified pixels by post-processing the results using noise reduction algorithms, such as morphological operations (`imdilate`, `imerode`, `imopen`, `imclose`). For example, use a morphological close operation to reduce the noise in the green field segmented image.

```
greenFieldLowNoise = getSegmentedImageClose(reshape(y(:,1), [imgRow, imgCol]), cImg);  
figure  
imshow(greenFieldLowNoise)
```




To improve fuzzy classifier performance, you can:

- Use more training data.
- Learn color patterns of multiple pixels instead of learning individual pixel color.
- Increase the length of the gradient feature vector, in other words, use gradient values of more than three successive pixels.
- Add more MFs to the FIS for pixel classification.
- Use type-2 FIS.
- Use a validation tolerance, a larger window size, and higher k-fold values for cross validation.
- Tune the parameters of the constructed FIS tree `segFIS`.

Local Functions

```
function data = getColorInputData(img)
% Create RGB input data from an image for training.

[row,col,depth] = size(img);
data = zeros(row*col,depth);
id = 0;
for i = 1:row
    for j = 1:col
        id = id + 1;
        for k = 1:depth
            data(id,k) = img(i,j,k);
        end
    end
end
end
```

```

end

function [rmse,actY] = calculateRMSE(fis,x,y)
% Calculate root mean squared error for FIS output.

% Specify options for FIS evaluation
persistent evalOptions
if isempty(evalOptions)
    evalOptions = evalfisOptions("EmptyOutputFuzzySetMessage","none", ...
        "NoRuleFiredMessage","none","OutOfRangeInputValueMessage","none");
end

% Evaluate FIS
actY = evalfis(fis,x,evalOptions);

% Calculate RMSE
del = actY - y;
rmse = sqrt(mean(del.^2));

end

function cImg = getSegmentedImage(y,cImg)
% Segment an image using classifier output by creating a binary image
% using a 0.5 threshold.

id = y >= 0.5;
y(id) = 1;
y(~id) = 0;

cImg(:,:,1) = cImg(:,:,1).*y;
cImg(:,:,2) = cImg(:,:,2).*y;
cImg(:,:,3) = cImg(:,:,3).*y;

end

function y = normMat(x)
% Normalize array elements to the range [0 1].

tmp = x(:);
mn = min(tmp);
mx = max(tmp);
d = (mx-mn);
y = (x-mn);
if d>0
    y = y/d;
end

end

function data = getGradientInputData(x)
% Create gradient input data for training.

x = x(:);
n = 3; % Three successive gradient values.
data = zeros(length(x),n);

% Specify complete input vectors.
for i = n:length(x)

```

```
    data(i,:) = x(i-n+1:i)';
end

% Approximate missing elements in the incomplete input vector.
for i = n-1:-1:1
    right = x(1:i)';
    m = n - i;
    left = repmat(right(1),[1 m]);
    data(i,:) = [left right];
end

end

function cImg = getSegmentedImageClose(y,cImg)
% Segment an image using classifier output by creating a binary image
% using a 0.5 threshold.

id = y >= 0.5;
y(id) = 1;
y(~id) = 0;

se = strel('disk',1);
y = imclose(y,se);

cImg(:,:,1) = cImg(:,:,1).*y;
cImg(:,:,2) = cImg(:,:,2).*y;
cImg(:,:,3) = cImg(:,:,3).*y;

end
```

See Also

[tunefis](#) | [getTunableSettings](#) | [sugfis](#) | [fistree](#)

More About

- “Tuning Fuzzy Inference Systems” on page 3-2
- “Fuzzy Trees” on page 2-52


Autonomous Parking Using Fuzzy Inference System

This example shows how to tune a fuzzy inference system (FIS) for an autonomous parking application with nonholonomic constraints.

Autonomous parking is an essential capability of intelligent vehicles (autonomous cars). Nonholonomic kinematics impose additional constraints on autonomous parking, where a car cannot move sideways and instead uses a curving motion.

Kinematic Model

The following figure shows the kinematics of a nonholonomic car with a standard Ackermann steering mechanism.



The kinematic model has the following parameters.

- θ is the current orientation of the car with respect to a global reference frame.
- ϕ is the steering angle with respect to the car orientation.
- F is the front wheel center, (x_f, y_f) .
- R is the rear wheel center, (x_r, y_r) .
- $|RF|$ is the length of the wheelbase.
- O is the center of curvature for the car.
- $|OR|$ is the radius of curvature for the car.

In this model, the rear wheel orientation is fixed and parallel to the car body. That is, the rear wheels have the same orientation as the car, θ . The front wheels are parallel to each other and rotate with the steering angle ϕ . The steering angle is constrained to be between $-\Phi$ and $+\Phi$. For this example, Φ is 30 degrees.

The front and rear wheel centers have the following relationship.

$$x_f - x_r = |RF| \cdot \cos(\theta)$$

$$y_f - y_r = |RF| \cdot \sin(\theta)$$

The kinematic equations for the front wheel center velocity and car orientation velocity are as follows, where s is the speed of the car.

$$\dot{x}_f = s \cdot \cos(\theta + \phi)$$

$$\dot{y}_f = s \cdot \sin(\theta + \phi)$$

$$\dot{\theta} = \frac{s \cdot \sin(\phi)}{|RF|}$$


Autonomous Parking

The minimum radius of curvature (OR) for a car depends on the wheelbase length (RF). This minimum radius constrains the motion of the car during parking maneuvers.

When a human driver parks, they often fail to maintain the required car speed and orientation when approaching an empty parking space. To successfully park without a collision, they must compensate by switching between forward and backward motion while adjusting the speed and steering angle of the car.

Human drivers do not consciously perform geometric computations based on the kinematic model of their car. Instead, based on their own trial-and-error experience, they use natural rules and reasoning to understand the constraints of their car within a parking situation. You can use fuzzy systems to model such rule-based reasoning.

This example uses the following environment to simulate head-on parking of a nonholonomic car.




Here:

- The simulation environment is a 45-by-15 foot parking lot.
- The hatched area shows occupied parking spots.
- The empty parking spot is of 6-by-7 feet.
- The car is 5-by-3 feet and the length of the wheelbase ($|RF|$) is 3 feet, providing a 1 foot offset from the wheelbase to both the front and rear of the car.

This example assumes the following.


- The car is equipped with an intelligent system that can detect an empty parking spot and then stop the car near the starting edge of the parking spot.
- The autonomous parking system takes control of the car after it stops. Ideally, at the starting position, the car is almost vertically centered in the road and parallel to the road ($\theta = 0$ deg or $\theta = 180$ deg).
- Due to the constantly changing nature of a parking lot, the kinematic motion constraints, and the physical car attributes, a car does stop at the exact desired position and orientation. Therefore, the parking system assumes that the car stops somewhere in front of the empty parking spot with $\theta \approx 0$ or $\theta \approx 180$ deg and with unequal space on either side of the car.
- To avoid collisions, the car is equipped with range sensors to provide range data for the front, rear, left, and right sides of the car. The following figure shows an example of the range data obtained from the sensors in the simulation environment.




- The maximum sensor range is assumed to be 50ft, which covers the entire simulation environment.

Human Reasoning for Car Parking

Generally, as shown in the following figure, a human driver maintains the appropriate speed and steering angle when approaching an empty head-on parking spot. In this case, they can park without any forward and backward oscillating motions.



However, sometimes a driver fails to maintain the desired speed and steering angle for oscillation-free parking. As shown in the following example, the driver must then compensate using back-and-forth motions.



In this case, the driver:

- 1 Turns right and moves forward.
- 2 Fails to enter the parking spot, since the front of the car approaches the car in the occupied space.
- 3 Turns left and backs up to make enough room to enter the parking spot
- 4 Moves forward to enter the parking spot while adjusting the car orientation to align with the parking direction.
- 5 Stops when the front of the car is a safe minimal distance from the end of the parking spot and the vehicle is aligned with the parking spot (90 deg orientation within the simulation environment).

The following section uses these motion patterns to construct fuzzy systems for autonomous parking.

Generate Training Data

For tuning the fuzzy systems, this example artificially generates training data using the kinematic model of the car and the motion patterns described in the previous section. The data generation process uses the following discrete form of the kinematic model, where Δt is 0.1 seconds.

$$x_f(k+1) = x_f(k) + \Delta t \cdot s(k+1) \cdot \cos(\theta(k) + \phi(k+1))$$

$$y_f(k+1) = y_f(k) + \Delta t \cdot s(k+1) \cdot \sin(\theta(k) + \phi(k+1))$$

$$\theta(k+1) = \frac{s(k+1) \cdot \sin\phi(k+1)}{|RF|}$$

$$x_r(k+1) = x_f(k+1) - |RF| \cdot \cos\theta(k+1)$$

$$y_r(k+1) = y_f(k+1) - |RF| \cdot \sin\theta(k+1)$$

The steering angle (ϕ) and speed (s) values are generated based on the typical human driving patterns discussed previously. The steering angle and speed are constrained to the following limits.

$$-\Phi \leq \phi \leq \Phi, \Phi = 30^\circ$$

$$-3 \cdot S \leq s \leq S, S = 5 \frac{\text{ft}}{\text{sec}}$$

In order to make space for safe turning, the backward motion uses a higher speed when the car gets closer to the occupied space. Alternatively, the car can use the same speed for longer periods when going backwards to make adequate space for safe turning.

Load the training data structure.

```
trainingData = load('trainingData');
```

Each training data point includes five inputs.

- Angular deviation ($\Delta\theta$) between the car orientation and the parking spot orientation
- Minimum distances to the front (d_{front}), left (d_{left}), rear (d_{rear}), and right (d_{right}) of the car

Each training data point includes two outputs.

- Steering angle (ϕ)
- Speed (s) of the car

Since the angular deviation and distance values have different units and scales, the training data is normalized to the range [0 1]. Doing so removes any sensitivity of the cost function to errors in the larger magnitude inputs. The training data structure contains both the original input and output values (x and y) and their normalized values (xn and yn).

During data generation, a successful parking condition is achieved when the car reaches a minimum safe distance from the end of the parking spot and is aligned with the parking direction.


Construct and Train Initial Fuzzy Systems

This example uses a FIS tree as the fuzzy parking system. The first stage of the tuning process is to construct and train the initial FISs that you later assemble into a FIS tree. You then improve performance by fine tuning the parameters of the entire FIS tree.

To construct and tune the initial fuzzy systems, this example uses ANFIS, which provides faster convergence compared to other tuning methods.

The design of the FIS tree and its component fuzzy systems addresses the following considerations.

- The FIS tree has five inputs and two outputs that match the values in the training data set.
- Since ANFIS supports a single output, construct separate fuzzy subsystems for steering angle (ϕ) and speed (s).
- For better performance, each of these subsystems uses separate FISs for forward and backward motion.
- Combine the forward and backward motion controllers for each subsystem using an additional FIS.



Train the forward motion controller for steering, `forwardPhiFIS`, using the training input and output data. To do so, first extract the normalized steering angle training data.

```
forwardPhi = trainingData.yn(:,1);
```

Then, since this system is only for forward motion, set the steering angle output values to 0 for negative speed values.

```
negSpeedId = trainingData.y(:,2) < 0;  
forwardPhi(negSpeedId) = 0;
```

Create options for ANFIS training and configure the display to show only the final training results.

```
aoptions = anfisOptions;  
aoptions.DisplayANFISInformation = false;  
aoptions.DisplayErrorValues = false;  
aoptions.DisplayStepSize = false;
```

Use three MFs for the first input ($\Delta\theta$), since it has both positive and negative values. Use two MFs for the distance inputs.

```
aoptions.InitialFIS = [3 2 2 2 2];
```

Train forwardPhiFIS.

```
forwardPhiFIS = anfis([trainingData.xn forwardPhi],aoptions);
```

```
Minimal training RMSE = 0.100129
```

In a similar manner, train the forward speed controller, forwardSpeedFIS.

```
forwardSpeed = trainingData.yn(:,2);  
forwardSpeed(negSpeedId) = 0;
```

```
forwardSpeedFIS = anfis([trainingData.xn forwardSpeed],aoptions);
```

```
Minimal training RMSE = 0.161479
```

Next, tune the backward motion controllers for steering angle and speed, backwardPhiFIS and backwardSpeedFIS, respectively. In this case, set the output values to 0 for positive speed values.

Train backwardPhiFIS.

```
backwardPhi = trainingData.yn(:,1);  
backwardPhi(~negSpeedId) = 0;
```

```
backwardPhiFIS = anfis([trainingData.xn backwardPhi],aoptions);
```

```
Minimal training RMSE = 0.112362
```

Train backwardSpeedFIS.

```
backwardSpeed = trainingData.yn(:,2);  
backwardSpeed(~negSpeedId) = 0;
```

```
backwardSpeedFIS = anfis([trainingData.xn backwardSpeed],aoptions);
```

```
Minimal training RMSE = 0.0642125
```

For each FIS, specify a corresponding FIS name.

```
forwardPhiFIS.Name = 'forwardPhiFIS';  
forwardSpeedFIS.Name = 'forwardSpeedFIS';  
backwardPhiFIS.Name = 'backwardPhiFIS';  
backwardSpeedFIS.Name = 'backwardSpeedFIS';
```

Next, train phiFIS, which combines the forward and backward steering angle values generated by forwardPhiFIS and backwardPhiFIS. To generate input training data for phiFIS, evaluate forwardPhiFIS and backwardPhiFIS using the normalized input training data.

```
eoptions = evalfisOptions;
eoptions.EmptyOutputFuzzySetMessage = 'none';
eoptions.NoRuleFiredMessage = 'none';
eoptions.OutOfRangeInputValueMessage = 'none';

forwardPhi = evalfis(forwardPhiFIS,trainingData.xn,eoptions);
backwardPhi = evalfis(backwardPhiFIS,trainingData.xn,eoptions);
```

Use five MFs for each input. In this case, you can use a higher number of MFs, since phiFIS has only two inputs.

```
aoptions.InitialFIS = 5;
```

Train phiFIS using the generated input data and the normalized output training data.

```
phiFIS = anfis([forwardPhi backwardPhi trainingData.yn(:,1)],aoptions);
```

```
Minimal training RMSE = 0.120349
```

```
phiFIS.Name = 'phiFIS';
```

Similarly, train speedFIS, which combines the forward and backward speed values generated by forwardSpeedFIS and backwardSpeedFIS, respectively. To generate input training data for speedFIS, evaluate forwardSpeedFIS and backwardSpeedFIS using the normalized input training data.

```
forwardSpeed = evalfis(forwardSpeedFIS,trainingData.xn,eoptions);
backwardSpeed = evalfis(backwardSpeedFIS,trainingData.xn,eoptions);

speedFIS = anfis([forwardSpeed backwardSpeed trainingData.yn(:,2)],aoptions);
```

```
Minimal training RMSE = 0.0969036
```

```
speedFIS.Name = 'speedFIS';
```

Construct and Tune FIS Tree

The next stage of the tuning process is to construct and tune a fuzzy tree using the previously tuned component FISs. To create the FIS tree, first define the connections between the component FISs according to the overall FIS tree design.

```
connections = [...
    "forwardPhiFIS/output" "phiFIS/input1"; ...
    "backwardPhiFIS/output" "phiFIS/input2"; ...
    "forwardSpeedFIS/output" "speedFIS/input1"; ...
    "backwardSpeedFIS/output" "speedFIS/input2"; ...
    "forwardPhiFIS/input1" "backwardPhiFIS/input1"; ...
    "forwardPhiFIS/input1" "forwardSpeedFIS/input1"; ...
    "forwardPhiFIS/input1" "backwardSpeedFIS/input1"; ...
    "forwardPhiFIS/input2" "backwardPhiFIS/input2"; ...
    "forwardPhiFIS/input2" "forwardSpeedFIS/input2"; ...
    "forwardPhiFIS/input2" "backwardSpeedFIS/input2"; ...
    "forwardPhiFIS/input3" "backwardPhiFIS/input3"; ...
    "forwardPhiFIS/input3" "forwardSpeedFIS/input3"; ...
```

```

    "forwardPhiFIS/input3" "backwardSpeedFIS/input3"; ...
    "forwardPhiFIS/input4" "backwardPhiFIS/input4"; ...
    "forwardPhiFIS/input4" "forwardSpeedFIS/input4"; ...
    "forwardPhiFIS/input4" "backwardSpeedFIS/input4"; ...
    "forwardPhiFIS/input5" "backwardPhiFIS/input5"; ...
    "forwardPhiFIS/input5" "forwardSpeedFIS/input5"; ...
    "forwardPhiFIS/input5" "backwardSpeedFIS/input5"; ...
];

```

Construct the FIS tree.

```

fuzzySystems = [...
    forwardPhiFIS backwardPhiFIS ...
    forwardSpeedFIS backwardSpeedFIS ...
    phiFIS speedFIS];
fisT = fistree(fuzzySystems,connections);

```

Next, fine-tune both the MF and rule parameter values of `fisT`. For better performance, tune the fuzzy system parameters for individual outputs.

- First, tune the FIS parameters for steering angle.
- Second, tune the FIS parameters for speed.

To tune FIS tree parameters for one output without considering the other output value, you can temporarily remove the other output from the FIS tree.

To tune the FIS tree for the steering angle output, remove the second output from `fisT` and get tunable settings from `forwardPhiFIS`, `backwardPhiFIS`, and `phiFIS`.

```

fisTin1 = fisT;
fisTin1.Outputs(2) = [];
[in,out,rule] = getTunableSettings(fisTin1,'FIS',...
    ["forwardPhiFIS" "backwardPhiFIS" "phiFIS"]);

```

Create a tuning option set.

```
toptions = tunefisOptions;
```

Use the `patternsearch` method for fine-tuning and set the maximum iteration number to 10. If you have Parallel Computing Toolbox™ software, you can improve the speed of the tuning process by setting `toptions.UseParallel` to `true`. If you do not have Parallel Computing Toolbox software, set `options.UseParallel` to `false`, which is the default value.

```

toptions.Method = 'patternsearch';
toptions.MethodOptions.MaxIterations = 10;

```

To improve the pattern search results, set the method option `UseCompletePoll` to `true`.

```
toptions.MethodOptions.UseCompletePoll = true;
```

For reproducibility, set the random number generator seed to default.

```
rng('default')
```

Training can be computationally intensive and take several hours to complete. To save time, load a pretrained FIS tree by setting `runtunefis` to `false`. To run the tuning, you can set `runtunefis` to `true`.

```
runtunefis = false;
```

Tune the FIS tree.

```
if runtunefis
    fisTout1 = tunefis(fisTin1,[in;out;rule],...
        trainingData.xn,trainingData.yn(:,1),toptions);
else
    preTunedFIST = load('tunedFIST');
    fisTout1 = preTunedFIST.fisTout1;
end
```

Next, tune the other FIS tree output by first removing the speed output and adding the steering angle output. Then, get tunable settings from forwardSpeedFIS, backwardSpeedFIS, and speedFIS.

```
fisTin2 = fisTout1;
fisTin2.Outputs(1) = "speedFIS/output";
[in,out,rule] = getTunableSettings(fisTin2,'FIS',...
    ["forwardSpeedFIS" "backwardSpeedFIS" "speedFIS"]);
```

Tune the FIS tree. After training, reset the outputs of the FIS tree.

```
if runtunefis
    rng('default')
    fisTout = tunefis(fisTin2,[in;out;rule],...
        trainingData.xn,trainingData.yn(:,2),toptions);
    fisTout.Outputs(1) = "phiFIS/output";
    fisTout.Outputs(2) = "speedFIS/output";
else
    fisTout = preTunedFIST.fisTout;
end
```

Check the individual training errors (root mean squared error) of the outputs.

```
err = trainingData.yn - evalfis(fisTout,trainingData.xn,eoptions);
err = err.*err;
rmsePhi = sqrt(mean(err(:,1)))

rmsePhi = 0.1186

rmseSpeed = sqrt(mean(err(:,2)))

rmseSpeed = 0.0967
```

The performance is not meaningfully better compared to the ANFIS-trained fuzzy system.

Autonomous Parking Simulation

The training data contains a limited set of initial conditions. Therefore, the tuned FIS tree is valid for the following conditions.

- The front of the car must be initially located in front of the parking spot with $21 \leq x_f \leq 25$.
- The car must be closely aligned with the road direction, that is, the initial car orientation must be $\theta \approx 0$ or $\theta \approx 180$ deg.
- The car must initially be at least 1.5 ft from either road edge. That is, $d_{left} > 1.5$ ft and $d_{right} > 1.5$ ft.


Parking from Right Side

The tuned FIS is trained for head-on parking from the right side ($\theta \approx 180$ deg) of the road.

The following result shows a head-on parking simulation for $x_f = 24$ ft, $y_f = 4.5$ ft, and $\theta = 180$ deg.

```
parkFromRight = true;
xf = 24;
yf = 4.5;
theta = 180;
figure
simulateParking(parkFromRight, fisTout, trainingData, xf, yf, theta)
```


Parked



Simulate parking for a different initial condition where $x_f = 22$ ft, $y_f = 5$ ft, and $\theta = 170$ deg.

```
parkFromRight = true;
xf = 22;
yf = 5;
theta = 170;
figure
simulateParking(parkFromRight, fisTout, trainingData, xf, yf, theta)
```

Parked



In both cases, the car can autonomously park using the back-and-forth motion pattern. However, the car does not maintain equal distance values on the left and right sides of the parking space. This behavior is common for human drivers who do not generally park in the exact middle of a parking space. Instead, they use a safe distance from each side.

Parking from Left Side


You can use the same fuzzy system for head-on parking from the left side ($\theta \approx 0$ deg). To do so, set `parkFromRight` to `false`, which causes `simulateParking` to change the input values as follows:

- Switch the sign of the angular deviation input $\Delta\theta$.
- Switch the distance inputs for the left (d_{left}) and right (d_{right}) sides.

Simulate autonomous parking from the left side for $x_f = 22$ ft, $y_f = 5.5$ ft, and $\theta = 0$ deg.

```
parkFromRight = false;
xf = 22;
yf = 5;
theta = 0;
figure
simulateParking(parkFromRight, fisTout, trainingData, xf, yf, theta)
```


Parked



Simulate parking for another initial condition where $x_f = 22$ ft, $y_f = 5.5$ ft, and $\theta = 0$ deg.

```
parkFromRight = false;  
xf = 23.8;  
yf = 5.2;  
theta = 7;  
figure  
simulateParking(parkFromRight, fisTout, trainingData, xf, yf, theta)
```

Parked




In this case, similar to the right side parking results, the car follows a back-and-forth motion to safely park the car.


Conclusion

The current fuzzy system design has the following shortcomings:

- The generated data considers only two motion patterns for autonomous parking. Therefore, the autonomous parking system has limited robustness and does not represent all common skills of a human driver. For example, the following figure shows another common scenario where the driver moves back and turns right to make space on the right from the occupied space.



- The generated data uses a ± 30 deg limit for steering angles. The resulting high radius of curvature increases the difficulty of parking without oscillation.
- The sensor model used in this example is a trivial occupancy detection model where the range values are radially detected from the center of the car. Furthermore, when range data is similar from each corner of the car, the fuzzy system can produce unexpected results and local optima within the simulation. A better alternative is to model range data normal to each side of the car, as shown in the following figure. In this case, the distance measurements from each side of the car are independent from each other.



- ANFIS supports only Sugeno FISs, which might not always produce a smooth control surface.

To update the FIS tree design, you can consider the following potential changes.

- Use Mamdani FISs, which support additional tuning methods beyond ANFIS.
- Design the initial rule base of the fuzzy inference systems using human reasoning and then tune with the training data.
- Use a custom cost function to automatically generate data and optimize the parking trajectory using reward-based parking simulation. For an example, see “Tune Fuzzy Robot Obstacle Avoidance System Using Custom Cost Function” on page 3-71.

See Also

tunefis | getTunableSettings | fistree

More About

- “Tuning Fuzzy Inference Systems” on page 3-2
- “Fuzzy Trees” on page 2-52


Design Controller for Artificial Pancreas Using Fuzzy Logic

This example shows how to design and optimize a fuzzy inference system (FIS) tree to control an artificial pancreas. The artificial pancreas regulates the blood glucose level of an individual with type 1 diabetes using subcutaneous infusion of insulin.

A FIS tree is a distributed, hierarchical representation of a monolithic FIS with multiple FISs, each with a smaller rule base. Hence, a FIS tree provides easier understanding of the inference process and allows faster performance optimization with a smaller number of tunable parameters as compared to a monolithic FIS.

Type 1 diabetes is a widespread health problem that occurs when the pancreas fails to produce enough insulin to regulate blood glucose levels. An uncontrolled high blood glucose level (hyperglycemia) can cause significant damage to the human body. Therefore, an artificial pancreas system that continuously monitors and regulates blood glucose level with appropriate subcutaneous insulin infusion is a major goal in healthcare device development.

The following figure, which is adapted from [1], shows the components of an artificial pancreas system.



The continuous glucose monitoring (CGM) system periodically measures the blood glucose level of the diabetic patient and passes this information to a controller. The controller drives an insulin pump, which injects an optimal insulin dosage to the patient, thus regulating the blood glucose level. The controller provides the following two types of insulin dosage.

- Basal dosage — Long-term small amount of insulin for the fasting period of a diabetic patient
- Bolus dosage — Short-term large amount of insulin necessary for absorption of a major meal


Therefore, the task for the controller is to generate corrective insulin doses for the following cases.

- Hyperglycemia — When the blood sugar level is high, the controller provides a high insulin dose in bolus mode. Generally, this dose is in the range of 125 to 200 mg/dL, which can vary depending on the fasting and meal conditions for the patient.
- Hypoglycemia — When the blood glucose level is low, generally less than 50-70 mg/dL, the controller stops providing insulin.
- Normal condition — In the normal condition, the blood glucose level is generally in the range of 80 to 100 mg/dL and the controller provides a low insulin dosage in basal mode.

Artificial Pancreas Model

The `artificialPancreasWithFISTreeControl` Simulink® model implements an artificial pancreas system.

```
model = 'artificialPancreasWithFISTreeControl';
load_system(model)
```




This model contains the following subsystems.

- Diabetic Patient — Models the kinetics of insulin and its effect on glucose in the human body for type-1 diabetes as described in [2] and [3].
- Meal — Generates glucose absorption from meals. For this example, the meals are scheduled for the 1st, 5th, and 12th hours of the day.
- Glucose Monitoring System — Provides noise-free samples of blood glucose levels every 5 minutes using a perfect transducer.
- Controller — Generate corrective insulin doses using a hierarchical FIS tree.
- Insulin Pump — Infuses the exact amount of insulin recommended by the FIS controller using an ideal pump model.

To view how the blood glucose level of a diabetic patient changes when the body absorbs glucose without corrective insulin infusion, simulate the model with a constant zero control action. To do so, open the control loop by setting `closeLoop` to 0.

```
closeLoop = 0;
openLoopOutput = sim(model);
plotAbsorbedAndBloodGlucose(openLoopOutput)
```



Without corrective insulin infusion, the patient blood glucose level increases and remains in a hyperglycemic state.

Close the control loop for tuning and simulation.

```
closeLoop = 1;
```

Create FIS Tree Controller Structure

The controller has the following inputs, as described in [4].

- Blood glucose level (mg/dL)
- Rate of change of blood glucose level (mg/dL/min)
- Acceleration rate of blood glucose level (mg/dL/min/min).

The output of the controller is an optimal insulin infusion dosage that maintains the blood glucose level of a diabetic patient at a normal level.

To produce an optimal insulin dosage based on the observed inputs, the fuzzy controller described in [4] uses expert knowledge to construct a single FIS with 75 rules. However, creating a large rule base using expert knowledge is a complicated process due to the manual construction of each fuzzy rule for all combinations of input membership functions (MFs).

Alternatively, using a FIS tree produces a system with multiple FISs, each with a smaller rule base. The hierarchical structure of the FIS tree and the smaller rule bases allow for a more intuitive understanding of the inference process.

This example uses an incremental design approach to combine the controller inputs using two Mamdani FIS objects in an incremental tree structure. For more information on fuzzy tree structures, see “Fuzzy Trees” on page 2-52.

The blood glucose level and its rate of change both contribute more to the control actions compared to the acceleration rate, which is often small and can create noise in the output. Therefore, in the first level of the FIS tree, you precalculate the insulin infusion rate `Precalculated_Dose` by combining the effects of the blood glucose level `BG_Level` and its rate of change `BG_Rate`. The acceleration rate `BG_Accel` is included in the second layer of the FIS tree.

Create the FIS (`fis1`) for the first level of the tree structure. The inputs of `fis1` each use three uniformly distributed triangular MFs. The output of `fis1` uses five such MFs, named as follows:

- For the input `BG_Level`, L, M, and H for low, medium, and high levels, respectively
- For the input `BG_Rate`, N, Z, and P for negative, zero, and positive rates, respectively
- For the output `Precalculated_Dose`, L, M, and H, plus VL for very low and VH for very high dosages


```
% Specify the maximum dose level.
maxDose = 2;

% Define membership function names for the input variables.
mfNames1 = ["L", "M", "H"]; % Low, Medium, High
mfNames2 = ["N", "Z", "P"]; % Negative, Zero, Positive

% Create first FIS.
fis1 = mamfis('Name', 'fis1', 'NumInputs', 2, 'NumOutputs', 1, ...
    'NumInputMFs', 3, 'NumOutputMFs', 5);

% Configure input and output variables.
fis1 = updateInput(fis1, 1, 'BG_Level', [80 120], mfNames1);
fis1 = updateInput(fis1, 2, 'BG_Rate', [-0.5 0.5], mfNames2);
fis1 = updateOutput(fis1, 1, 'Precalculated_Dose', [0 maxDose]);

figure
plotfis(fis1)
```




System fis1: 2 inputs, 1 outputs, 9 rules

Create the FIS (fis2) for the second level of the tree. Using fis2, you generate the final insulin dosage by combining the precalculated dose from the first layer with the effect of the blood glucose acceleration rate. In this case, the inputs and the output also use three and five uniformly distributed triangular MFs, respectively.

```
% Create second FIS.
fis2 = mamfis('Name','fis2','NumInputs',2,'NumOutputs',1, ...
    'NumInputMFs',3,'NumOutputMFs',5);

% Configure input and output variables.
fis2 = updateInput(fis2,1,'Precalculated_Dose',[0 maxDose],mfNames1);
fis2 = updateInput(fis2,2,'BG_Accel',[-0.005 0.005],mfNames2);
fis2 = updateOutput(fis2,1,'Insulin_Dose',[0 maxDose]);

figure
plotfis(fis2)
```





System fis2: 2 inputs, 1 outputs, 9 rules

Combine fis1 and fis2 into a FIS tree structure.

```
connection = [fis1.Name + "/" + fis1.Outputs(1).Name ...
             fis2.Name + "/" + fis2.Inputs(1).Name];
fisTInit = fistree([fis1 fis2],connection);
```

```
figure
plotfis(fisTInit)
```



The initial fuzzy systems are constructed with default fuzzy rules that are not tuned to produce optimal insulin dosages.

Tune Controller Rules

Once you have a FIS tree structure, you can optimize the controller behavior by tuning the rules and MF parameters of the component FIS objects. To do so, you can use the `tunefis` function.

In general, uniformly distributed MFs provide a meaningful initial condition for tuning a fuzzy system. Therefore, as an initial tuning step, you can learn the rules of the FIS objects while keeping their default MF parameters.

To learn the rules, first get the tunable settings from the fuzzy systems.

```
[in,out,rule] = getTunableSettings(fisTInit);
```

Next, update the rule settings to optimize only the rule consequents. By doing so, you keep the existing rule antecedents, which already include all possible input MF combinations for their corresponding FIS inputs.

```
for rId = 1:numel(rule)
    rule(rId).Antecedent.Free = false;
end
```

Create an option set for the tuning process.

```
options = tunefisOptions;
```

Use the default genetic algorithm tuning method for learning the rules. Set the maximum number of generations to 3 and use a population size of 100.

```
options.MethodOptions.MaxGenerations = 3;
options.MethodOptions.PopulationSize = 100;
```

Next, create a cost function to evaluate each candidate rule base. At the end of the optimization process, the rule base with the minimum cost is selected for the fuzzy systems in the FIS tree.

For this example, the cost function (`costFcn.m`) simulates the `artificialPancreasWithFISTreeControl` model using the candidate rule base. Using the resulting simulation output, the cost function computes the cost using the following steps.

- 1** Calculate errors in the observed glucose level from a nominal glucose level.
- 2** If the error value is negative (glucose below the nominal level), set the error value to a high value.
- 3** Calculate the cost as the root mean square of the error values.

Using this cost function, the tuning process selects rule bases that maintain a normal condition and avoid high glucose levels. Also, the high error values used in step 2 help discard rule bases that produce low blood glucose levels.

```
% Specify the nominal and minimum glucose levels.
refLevel = 90;
minLevel = 80;
```

```
% Calculate error from the nominal value.
err = glucose - refLevel;
```

```
% Specify high error values for the glucose levels below the nominal level.
err(glucose<minLevel) = 100;
```

```
% Calculate cost as the root mean square of the error.
errSquare = err.^2;
meanSquare = mean(errSquare);
cost = sqrt(meanSquare);
```

Tuning is a time-consuming process, so for this example, load a pretuned FIS tree. To tune the FIS tree yourself instead, set `runtunefis` to true.

```
runtunefis = false;
```

```
% Load pretuned FIS tree data
data = load('fuzzyPancreasExampleData.mat');
```

```
minData = MinCostData;
wsVars = ["fisT" "closeLoop"];
minLevel = 80;
refLevel = 90;
if runtunefis
    rng('default')
    fisTRuleTuned = tunefis(fisTInit,rule,...
        @(fis)costFcn(fis,model,minLevel,refLevel,wsVars,minData),options);
else
    fisTRuleTuned = data.fisTRuleTuned;
    minCost = costFcn(fisTRuleTuned,model,minLevel,refLevel,wsVars)
end
```


```
minCost = 26.3335
```

Simulate the model using the FIS tree with tuned rule bases.

```
fisT = fisTRuleTuned;
ruleTunedOutput = sim(model);
```

Plot the resulting regulated glucose levels and insulin infusion rate.

```
plotGlucoseAndInsulin(ruleTunedOutput,...
    'Blood Glucose and Insulin Dosage with Learned Rule Base')
```




With the tuned rule base, the glucose level is now maintained below 160 mg/dL, and it settles close to 90 mg/dL after the third meal. The controller generates a short-term high insulin dosage (bolus mode) at each meal time and a long-term reduced insulin dosage (basal mode) during the fasting periods.

Analyze and Modify Rule Base

To visualize the behavior of the tuned rule base, plot the control surface of each fuzzy system in the FIS tree.

```
figure('Position',[300 300 600 300]);
subplot(1,2,1)
gensurf(fisTRuleTuned.FIS(1))
title('Control Surface - fis1')
subplot(1,2,2)
gensurf(fisTRuleTuned.FIS(2))
title('Control Surface - fis2')
```



The following tables show the corresponding rule bases of `fis1` and `fis2`.

```
showRuleBase(fisTRuleTuned.FIS(1))
```

Rule base of `fis1`:

	BG_Rate: N	BG_Rate: Z	BG_Rate: P
BG_Level: L	Precalculated_Dose: VH	Precalculated_Dose: M	Precalculated_Dose: M
BG_Level: M	Precalculated_Dose: VL	Precalculated_Dose: M	Precalculated_Dose: H
BG_Level: H	Precalculated_Dose: M	Precalculated_Dose: H	Precalculated_Dose: VL

```
showRuleBase(fisTRuleTuned.FIS(2))
```

Rule base of `fis2`:

	BG_Accel: N	BG_Accel: Z	BG_Accel: P
Precalculated_Dose: L	Insulin_Dose: VH	Insulin_Dose: VL	Insulin_Dose: H
Precalculated_Dose: M	Insulin_Dose: VL	Insulin_Dose: L	Insulin_Dose: L
Precalculated_Dose: H	Insulin_Dose: L	Insulin_Dose: VL	Insulin_Dose: VH

These tables show that some of the control actions are nonintuitive. For example:

- For negative blood glucose rates of change, `fis1` does not increase insulin dosage monotonically with increasing blood glucose levels.
- For a high blood glucose level and a high positive blood glucose rate of change, `fis1` sets the insulin dosage to medium instead of very high.
- For negative blood glucose acceleration rates, `fis2` does not monotonically increase insulin dosage with increasing precalculated insulin dosage.
- For a low precalculated dose and a negative blood glucose acceleration rate, `fis2` sets the insulin dosage to very high instead of low.
- For a high precalculated dose and zero blood glucose acceleration rate, `fis2` sets the insulin dosage to very low instead of medium.

Update the rules by modifying their consequent values.

```
% Update fis1 rules.
fisTRuleUpdate = fisTRuleTuned;
fisTRuleUpdate.FIS(1).Rules(1).Description = ...
    "BG_Level==L & BG_Rate==N => Precalculated_Dose=VL";
fisTRuleUpdate.FIS(1).Rules(2).Description = ...
    "BG_Level==M & BG_Rate==N => Precalculated_Dose=M";
fisTRuleUpdate.FIS(1).Rules(3).Description = ...
    "BG_Level==H & BG_Rate==N => Precalculated_Dose=H";
fisTRuleUpdate.FIS(1).Rules(9).Description = ...
    "BG_Level==H & BG_Rate==P => Precalculated_Dose=VH";

% Update fis2 rules.
fisTRuleUpdate.FIS(2).Rules(1).Description = ...
    "Precalculated_Dose==L & BG_Accel==N => Insulin_Dose=VL";
fisTRuleUpdate.FIS(2).Rules(3).Description = ...
    "Precalculated_Dose==H & BG_Accel==N => Insulin_Dose=M";
fisTRuleUpdate.FIS(2).Rules(6).Description = ...
    "Precalculated_Dose==H & BG_Accel==Z => Insulin_Dose=M";
fisTRuleUpdate.FIS(2).Rules(7).Description = ...
    "Precalculated_Dose==L & BG_Accel==P => Insulin_Dose=L";
```

View the modified rule bases.

```
showRuleBase(fisTRuleUpdate.FIS(1))
```

Rule base of fis1:

	BG_Rate: N	BG_Rate: Z	BG_Rate: P
BG_Level: L	Precalculated_Dose: VL	Precalculated_Dose: M	Precalculated_Dose: M
BG_Level: M	Precalculated_Dose: M	Precalculated_Dose: M	Precalculated_Dose: H
BG_Level: H	Precalculated_Dose: H	Precalculated_Dose: H	Precalculated_Dose: VH


```
showRuleBase(fisTRuleUpdate.FIS(2))
```

Rule base of fis2:

	BG_Accel: N	BG_Accel: Z	BG_Accel: P
Precalculated_Dose: L	Insulin_Dose: VL	Insulin_Dose: VL	Insulin_Dose: L
Precalculated_Dose: M	Insulin_Dose: VL	Insulin_Dose: L	Insulin_Dose: L
Precalculated_Dose: H	Insulin_Dose: M	Insulin_Dose: M	Insulin_Dose: VH

Visualize the resulting FIS control surfaces.

```
figure('Position',[300 300 600 300]);
subplot(1,2,1)
gensurf(fisTRuleUpdate.FIS(1))
title('Control Surface - fis1')
subplot(1,2,2)
gensurf(fisTRuleUpdate.FIS(2))
title('Control Surface - fis2')
```



The control surfaces correspond to a more intuitive controller behavior.


To check if the updated rules improve the controller performance, simulate the model and plot the results. Compare the results with those of the controller with tuned MF parameters.

```

fisT = fisTRuleUpdate;
ruleUpdatedOutput = sim(model);

plotGlucoseAndInsulin([ruleTunedOutput ruleUpdatedOutput],...
    'Blood Glucose and Insulin Dosage with Updated Rule Base',...
    {'Learned rules', 'Updated rules'})

```



The controller with updated rules reduces the blood glucose levels compared to the tuned FIS tree controller.

Updating the rules reduces the value of the cost function.

```
minCost = costFcn(fisTRuleUpdate,model,minLevel,refLevel,wsVars)
```

```
minCost = 23.2702
```

Tune Membership Function Parameters


To further improve the controller performance, you can tune the MF parameters of the FIS tree.

To do so, use a local optimization method, such as pattern search. For this example, set the maximum number of optimization iterations to 10.

```
options.Method = 'patternsearch';
options.MethodOptions.MaxIterations = 10;
```

By default, each input variable has three uniformly distributed triangular MFs. For example, view the MFs for the first input of `fis1`.

```
figure
plotmf(fisTRuleUpdate.FIS(1),'input',1)
```

Configure the tunable settings for the input variables such that the leftmost and rightmost peaks remain unchanged during tuning.

```
for i = 1:4
    in(i).MembershipFunctions(1).Parameters.Free = [0 0 1];
    in(i).MembershipFunctions(end).Parameters.Free = [1 0 0];
end
```

Similarly, configure the tunable settings for the output variables. Each output variable has five triangular membership functions.

```
for i = 1:2
    out(i).MembershipFunctions(1).Parameters.Free = [0 0 1];
    out(i).MembershipFunctions(end).Parameters.Free = [1 0 0];
end
```

Tune the MF parameter values using the updated tunable settings.

```
if runtunefis
    figure
    reset(minData)
    rng('default')
    fisTMFTuned = tunefis(fisTRuleUpdate,[in;out],...
        @(fis)costFcn(fis,model,minLevel,refLevel,wsVars,minData),options);
else
    fisTMFTuned = data.fisTMFTuned;
    minCost = costFcn(fisTMFTuned,model,minLevel,refLevel,wsVars)
end
```

```
minCost = 22.0627
```


The MF tuning process reduces the value of the cost function further.

Simulate the model using the controller with tuned MF parameters.

```
fisT = fisTMFTuned;
mfTunedOutput = sim(model);
```

Plot the resulting regulated glucose levels and insulin infusion rate. Compare the results with those for the controller with tuned rule bases.

```
plotGlucoseAndInsulin([ruleUpdatedOutput mfTunedOutput],...
    'Blood Glucose and Insulin Dosage with Tuned MFs',...
    {'Updated rules', 'Tuned MFs'})
```



The tuned MF parameters improve the performance and reduce the minimum cost value.

To further improve controller performance you can implement the following modifications.

- Incrementally add additional inputs to the FIS tree controller, such as the patient weight and age, to provide a personalized insulin dosage.
- Use different numbers of MFs to balance performance and inference complexities.
- Use different tuning methods and iteration numbers to optimize the fuzzy system parameters.
- Use real world training data to tune the controller parameters.

```
% Close model.
close_system(model)
```

References

- [1] Grant, Paul. "A New Approach to Diabetic Control: Fuzzy Logic and Insulin Pump Technology." *Medical Engineering & Physics* 29, no. 7 (September 2007): 824-27. <https://doi.org/10.1016/j.medengphy.2006.08.014>.
- [2] Wilinska, M.E., L.J. Chassin, H.C. Schaller, L. Schaupp, T.R. Pieber, and R. Hovorka. "Insulin Kinetics in Type-1 Diabetes: Continuous and Bolus Delivery of Rapid Acting Insulin." *IEEE Transactions on Biomedical Engineering* 52, no. 1 (January 2005): 3-12. <https://doi.org/10.1109/TBME.2004.839639>.
- [3] Hovorka, Roman, Valentina Canonico, Ludovic J Chassin, Ulrich Haueter, Massimo Massi-Benedetti, Marco Orsini Federici, Thomas R Pieber, et al. "Nonlinear Model Predictive Control of Glucose Concentration in Subjects with Type 1 Diabetes." *Physiological Measurement* 25, no. 4 (August 1, 2004): 905-20. <https://doi.org/10.1088/0967-3334/25/4/010>.
- [4] Mauseth, Richard, Youqing Wang, Eyal Dassau, Robert Kircher, Donald Matheson, Howard Zisser, Lois Jovanovič, and Francis J. Doyle. "Proposed Clinical Application for Tuning Fuzzy Logic Controller of Artificial Pancreas Utilizing a Personalization Factor." *Journal of Diabetes Science and Technology* 4, no. 4 (July 2010): 913-22. <https://doi.org/10.1177/193229681000400422>.

Helper Functions

```
function fis = updateInput(fis,id,name,range,mfNames)
% Update FIS input with the specified parameter values.

fis.Inputs(id).Name = name;
fis.Inputs(id).Range = range;

for mfId = 1:length(mfNames)
    fis.Inputs(id).MembershipFunctions(mfId).Name = mfNames(mfId);
    params = range(1) + ...
        diff(range)*fis.Inputs(id).MembershipFunctions(mfId).Parameters;
    fis.Inputs(id).MembershipFunctions(mfId).Parameters = params;
end

end

function fis = updateOutput(fis,id,name,range)
% Update FIS output with the specified parameter values.

rangeDiff = diff(range);
fis.Outputs(id).Name = name;

% MF names - Very Low, Low, Medium, High, Very High
mfNames = [...
    "VL", "L", "M", "H", "VH"];

for mfId = 1:length(mfNames)
    fis.Outputs(id).MembershipFunctions(mfId).Name = mfNames(mfId);
    params = range(1) + ...
        rangeDiff*fis.Outputs(id).MembershipFunctions(mfId).Parameters;
    fis.Outputs(id).MembershipFunctions(mfId).Parameters = params;
end

end
```

```
% Extend output range values to fit the output MFs.  
left = fis.Outputs(id).MembershipFunctions(1).Parameters(1);  
right = fis.Outputs(id).MembershipFunctions(end).Parameters(end);  
fis.Outputs(id).Range = [left right];  
  
end
```

See Also

tunefis | getTunableSettings | fistree

More About

- “Tuning Fuzzy Inference Systems” on page 3-2
- “Fuzzy Trees” on page 2-52

Explain Black-Box Model Using Fuzzy Support System

This example shows how to develop a fuzzy inference support system that explains the behavior of a black-box model.


Using nondeterministic machine learning methods, such as deep learning, you can design a black-box model to estimate the input-output mapping for a given set of experimental or simulation data. However, the input-output relationship defined by such a black-box model is difficult to understand.

In such cases, a common approach is to create a transparent support system to explain the input-output relationships modeled by the a black box system.

A fuzzy inference system (FIS) is a transparent model that represents system knowledge using an explainable rule base. Since the rule base of a fuzzy system is easier for a user to intuitively understand, a FIS is often used as a support system to explain an existing black box model.

The following figure shows the general steps for developing a fuzzy support system from an existing black box with the assumption that the original training data of the black box is available.

- Tune a support FIS using the original training data for the black box.
- Compare the behavior of the black-box system and the FIS using test data.
- Examine the FIS rules to explain the behavior of the black-box system.



In general, you can use a fuzzy support system to explain different types of black-box models. For this example, the black-box model is implemented using a deep neural network (DNN), which requires Deep Learning Toolbox™ software.

Black-Box Model

The DNN model for this example imitates an automotive lane keeping assist (LKA) system implemented using model predictive control (MPC). A vehicle (ego car) equipped with an LKA system has a sensor, such as camera, that measures the lateral deviation and relative yaw angle between the

centerline of a lane and the ego car. The sensor also measures the current lane curvature and curvature derivative. Depending on the curve length that the sensor can view, the curvature in front of the ego car can be calculated from the current curvature and curvature derivative. The LKA system keeps the ego car travelling along the centerline of the lane by adjusting the front steering angle of the ego car. The goal for lane keeping control is to drive both lateral deviation and relative yaw angle close to zero. For more information on lane keeping using MPC, see “Lane Keeping Assist System Using Model Predictive Control” (Model Predictive Control Toolbox).

The DNN-based LKA system uses the following inputs to generate the output steering angle u^* .

- 1 Lateral velocity V_y m/s
- 2 Yaw angle rate r rad/s
- 3 Lateral deviation e_1 m
- 4 Relative yaw angle e_2 rad
- 5 Previous steering angle (control variable) u rad
- 6 Measured disturbance (road yaw rate: longitudinal velocity * curvature (ρ))

For more information on creating and training the DNN, see “Imitate MPC Controller for Lane Keeping Assist” (Reinforcement Learning Toolbox).

For this example, load the saved DNN model of an LKA system. `data` also contains the training and testing data along with pretrained FIS trees.

```
data = load('dataExplainDNN.mat');  
dnnLKA = data.trainedDNN;
```

The trained DNN predicts a steering angle based on the current input values to keep the car along the centerline of a lane. To make a prediction, use the `predict` function. For example, the following command predicts the steering angle when all input signals are zero.

```
steeringAngle = predict(dnnLKA,zeros(1,6))  
  
steeringAngle = single  
               -0.0195
```

However, the DNN model does not provide any explanation about how it derives the steering angle. The DNN model parameters are the steering angle generation algorithm in terms of hidden units and their associated parameters. Therefore, input-output relations cannot be described using the DNN structure alone.

```
figure  
plot(layerGraph(dnnLKA))
```



To explain the DNN model behavior, you can create and tune a fuzzy support system.

Create Initial Fuzzy Inference System

For an LKA controller with six inputs, a single monolithic FIS contains a large complex rule base that is difficult to interpret. As an alternative, you can create a FIS tree that incrementally combines input values using multiple FISs, each with a smaller rule base.

Create a FIS tree with four layers and five FISs. Each FIS has two inputs and one output. To create each component FIS, use the `constructFIS` helper function, which is shown at the end of this example.

```
numMFs = 2;
fis1 = constructFIS('fis1',numMFs, ...
    data.vRange,data.e1Range,data.uRange,'Vy','e1','u1');
fis2 = constructFIS('fis2',numMFs, ...
    data.rRange,data.e2Range,data.uRange,'r','e2','u2');
fis3 = constructFIS('fis3',numMFs, ...
    data.uRange,data.uRange,data.uRange,'u1','u2','u3');
fis4 = constructFIS('fis4',numMFs, ...
    data.uRange,data.uRange,data.uRange,'u3','u','u4');
fis5 = constructFIS('fis5',numMFs, ...
    data.uRange,data.dRange,data.uRange,'u4','d','u*');

fis = [fis1 fis2 fis3 fis4 fis5];
connections = [...
    fis1.Name+"/"+fis1.Outputs(1).Name fis3.Name+"/"+fis3.Inputs(1).Name; ...
```

```

    fis2.Name+"/"+fis2.Outputs(1).Name  fis3.Name+"/"+fis3.Inputs(2).Name; ...
    fis3.Name+"/"+fis3.Outputs(1).Name  fis4.Name+"/"+fis4.Inputs(1).Name; ...
    fis4.Name+"/"+fis4.Outputs(1).Name  fis5.Name+"/"+fis5.Inputs(1).Name ...
];

```

```

fisTin = fistree(fis,connections);


```

View the FIS tree structure.

```

showFISTree(fisTin)

```



In this FIS tree:

- The first layer uses two FISs: **fis1** and **fis2**, where **fis1** combines lateral velocity (V_y) and lateral deviation (e_1), and **fis2** combines yaw angle (r) and relative yaw angle (e_2) to predict expected steering angles u_1 and u_2 for the respective input values.
- The second layer uses **fis3** to combine the outputs of **fis1** and **fis2**, that is, **fis3** combines the effects of lateral displacement and yaw angle to produce a desired steering angle (u_3) for the LKA system.
- The third layer uses **fis4** to combine the effect of the previous steering angle (u) with the output of second layer to generate u_4 .
- The fourth layer combines the effect of the measured disturbance (d) with the desired steering angle predicted by the previous layers using **fis5**.

Each input of a FIS includes two membership functions (MFs) and each output includes four MFs. As a result, each FIS has four rules and the overall FIS tree has 20 rules.

Tune Fuzzy Inference System

For this example, you tune the FIS in two stages.

- 1 Establish the input-output relations for each FIS by learning by learning the output membership functions for each possible input combination.
- 2 Tune the MF parameters for the input and output variables of each FIS.

To learn the output membership functions for each rule, first obtain the rule parameter settings from the initial FIS `fisTin`.

```
[~,~,rule] = getTunableSettings(fisTin);
```

Then, specify that the antecedent membership functions are fixed during the tuning process.

```
for ct = 1:length(rule)
    rule(ct).Antecedent.Free = 0;
end
```

Create an option set for tuning. Use the default genetic algorithm (`ga`) as the tuning method. Set maximum stall generations to 5.

```
options = tunefisOptions;
options.MethodOptions.MaxStallGenerations = 5;
```

To visualize the convergence process, set the `PlotFcn` tuning method option to `gaplotbestf`.

```
options.MethodOptions.PlotFcn = @gaplotbestf;
```

To prevent overfitting, use k-fold cross validation with two partitions.

```
options.KFoldValue = 2;
```

Tuning is a time-consuming process, so for this example, load a pretuned FIS tree. To tune the FIS tree yourself instead, set `runtunefis` to `true`.

```
runtunefis = false;
```

Since the FIS tree input order is different than that of the black-box model, reorder the training data.

```
trainInputData = [data.Vy data.e1 data.r data.e2 data.uprev data.d];
```

Tune the fuzzy rules. For reproducibility, reset the random number generator using the default seed.

```
if runtunefis
    rng('default')
    fisToutR = tunefis(fisTin,rule,trainInputData,data.trainOutputData,options);
else
    fisToutR = data.fisToutR;
end
```

Evaluate the performance of the FIS using the training data. The `calculateRMS` helper function evaluates the input data using the specified FIS and computes the RMS error for the result.

```
rms = calculateRMS(fisToutR,trainInputData,data.trainOutputData)
```

```
rms = 0.3507
```

Display the tuned rule base of each FIS in the tree using the `showRules` helper function.

```
showRules(fisToutR)
```

fis1Rules	fis2Rules
<pre>"Vy==mf1 & e1==mf1 => u1=mf4 (1)" "Vy==mf2 & e1==mf1 => u1=mf3 (1)" "Vy==mf1 & e1==mf2 => u1=mf2 (1)" "Vy==mf2 & e1==mf2 => u1=mf1 (1)"</pre>	<pre>"r==mf1 & e2==mf1 => u2=mf1 (1)" "r==mf2 & e2==mf1 => u2=mf2 (1)" "r==mf1 & e2==mf2 => u2=mf4 (1)" "r==mf2 & e2==mf2 => u2=mf3 (1)"</pre>
fis3Rules	fis4Rules
<pre>"u1==mf1 & u2==mf1 => u3=mf3 (1)" "u1==mf2 & u2==mf1 => u3=mf4 (1)" "u1==mf1 & u2==mf2 => u3=mf1 (1)" "u1==mf2 & u2==mf2 => u3=mf2 (1)"</pre>	<pre>"u3==mf1 & u==mf1 => u4=mf1 (1)" "u3==mf2 & u==mf1 => u4=mf4 (1)" "u3==mf1 & u==mf2 => u4=mf1 (1)" "u3==mf2 & u==mf2 => u4=mf4 (1)"</pre>
fis5Rules	
<pre>"u4==mf1 & d==mf1 => u*=mf1 (1)" "u4==mf2 & d==mf1 => u*=mf4 (1)" "u4==mf1 & d==mf2 => u*=mf1 (1)" "u4==mf2 & d==mf2 => u*=mf4 (1)"</pre>	

`fis1`, `fis3`, `fis4`, and `fis5` do not use all of the output MFs. Hence, you can remove these unused output membership functions.

```

fisToutR2 = fisToutR;
for ct = 1:length(fisToutR2.FIS)
    numOutputMFs = length(fisToutR2.FIS(ct).Outputs(1).MembershipFunctions);
    numOutputMFUsed = unique([fisToutR2.FIS(ct).Rules.Consequent]);
    numOutputMFNotUsed = setdiff(1:numOutputMFs,numOutputMFUsed);
    if ~isempty(numOutputMFNotUsed)
        fisToutR2.FIS(ct).Outputs(1).MembershipFunctions(numOutputMFNotUsed) = [];
    end
end

```

Next, tune the input and output MF parameters. To do so, first get the input and output variable tunable settings for the FIS tree.

```
[in,out] = getTunableSettings(fisToutR2);
```

To improve the optimization results, increase the MF parameter ranges.

```

for fisId = 1:numel(fisToutR2.FIS)
    id = (fisId-1)*2;
    for inId = 1:numel(fisToutR2.FIS(fisId).Inputs)
        d = diff(fisToutR2.FIS(fisId).Inputs(inId).Range);
        l = fisToutR2.FIS(fisId).Inputs(inId).Range(1)-0.5*d;
        u = fisToutR2.FIS(fisId).Inputs(inId).Range(2)+0.5*d;
        for mfId = 1:numel(fisToutR2.FIS(fisId).Inputs(inId).MembershipFunctions)
            in(id+inId).MembershipFunctions(mfId).Parameters.Minimum = l;
            in(id+inId).MembershipFunctions(mfId).Parameters.Maximum = u;
        end
    end
end

```

Use the `patternsearch` algorithm for tuning the MF parameters.

```
options.Method = 'patternsearch';
```

To visualize the convergence process, set the `PlotFcn` tuning method option to `psplotbestf`.

```
options.MethodOptions.PlotFcn = @psplotbestf;
```

Tune the MF parameters.

```
if runtunefis
    rng('default')
    options.MethodOptions.MaxIterations = 10;
    fisToutMF = tunefis(fisToutR2,[in;out],trainInputData,data.trainOutputData,options);
else
    fisToutMF = data.fisToutMF;
end
```

The lower RMS error indicates that the fuzzy system performance improves after tuning the MF parameters.

```
rms = calculateRMS(fisToutMF,trainInputData,data.trainOutputData)
```

```
rms = 0.0506
```

Compare FIS to Black-Box Model

Before you can explain the behavior of the black-box model, first verify that the tuned FIS properly reproduces the behavior of the black-box model.

Evaluate the test data using the black-box DNN model and compute the RMS error for the result.

```
yDNN = predict(dnnLKA,data.testInputData);
d = yDNN - data.testOutputData;
rmseDNN = sqrt(mean(d.^2))
```

```
rmseDNN = single
0.0320
```

Evaluate the test data using the FIS and compute the RMS error for the result. Also, return the computed steering angles in `yFIS`.


```
testInputData = [data.testInputData(:,1) data.testInputData(:,3) ...
    data.testInputData(:,2) data.testInputData(:,4:6)];
[rmseFIS,yFIS] = calculateRMS(fisToutMF,testInputData,data.testOutputData);
rmseFIS
```

```
rmseFIS = 0.0518
```

The low RMS error values indicate that both the DNN and FIS closely reproduce the steering angles in the output training data. To further validate this result, plot the calculated steering angles for both systems over a subset of the training data.

```
start = 1;
stop = 50;
x = 1:length(data.testOutputData);
plot(x(start:stop),data.testOutputData(start:stop), ...
    x(start:stop),yDNN(start:stop), ...
    x(start:stop),yFIS(start:stop))
```

```
xlabel("Test Data Point")
ylabel("Steering Angle (radians)")
legend("Test Data", "DNN", "FIS")
```



The DNN and FIS both reproduce the expected steering angles from the training data.

Explain Black-Box Model Using FIS

To explain the black-box model, first specify meaningful names for the MFs of each FIS. Doing so improves the interpretability of the FIS behavior.

```
mfNames = {...
    ["negative" "positive"], ...
    ["negative" "zero" "positive"], ...
    ["negativeLow" "negative" "positive" "positiveHigh"] ...
};

for fisId = 1:numel(fisToutMF.FIS)
    for inId = 1:numel(fisToutMF.FIS(fisId).Inputs)
        numInputMFs = numel(fisToutMF.FIS(fisId).Inputs(inId).MembershipFunctions);
        names = mfNames{numInputMFs-1};
        for mfId = 1:numel(fisToutMF.FIS(fisId).Inputs(inId).MembershipFunctions)
            fisToutMF.FIS(fisId).Inputs(inId).MembershipFunctions(mfId).Name = names(mfId);
        end
    end

    numOutputMFs = numel(fisToutMF.FIS(fisId).Outputs(1).MembershipFunctions);
    names = mfNames{numOutputMFs-1};
    for mfId = 1:numOutputMFs
        fisToutMF.FIS(fisId).Outputs(1).MembershipFunctions(mfId).Name = names(mfId);
    end
end
```

end

View the FIS rules.

```
showRules(fisToutMF)
```

fis1Rules	fis2Rules
<pre>"Vy==negative & e1==negative => u1=positiveHigh (1)" "Vy==positive & e1==negative => u1=positive (1)" "Vy==negative & e1==positive => u1=negative (1)" "Vy==positive & e1==positive => u1=negativeLow (1)"</pre>	<pre>"r==negative & e2==negative => u2=negativeLow (1)" "r==positive & e2==negative => u2=negative (1)" "r==negative & e2==positive => u2=positive (1)" "r==positive & e2==positive => u2=positiveHigh (1)"</pre>
fis3Rules	fis4Rules
<pre>"u1==negative & u2==negative => u3=positive (1)" "u1==positive & u2==negative => u3=positiveHigh (1)" "u1==negative & u2==positive => u3=negativeLow (1)" "u1==positive & u2==positive => u3=negative (1)"</pre>	<pre>"u3==negative & u==negative => u4=negative (1)" "u3==positive & u==negative => u4=positive (1)" "u3==negative & u==positive => u4=negativeHigh (1)" "u3==positive & u==positive => u4=positiveHigh (1)"</pre>
fis5Rules	
<pre>"u4==negative & d==negative => u*=negative (1)" "u4==positive & d==negative => u*=positive (1)" "u4==negative & d==positive => u*=negative (1)" "u4==positive & d==positive => u*=positive (1)"</pre>	

You can make the following observations from the rule bases.

- Steering angle u_1 (output of `fis1`) is inversely proportional to lateral velocity (V_y) and deviation (e_1). For example, the first rule of `fis1` describes that the steering angle u_1 is `positiveHigh` (high positive value) when the lateral velocity (V_y) and deviation (e_1) are both `negative`.
- Steering angle u_2 (output of `fis2`) is proportional to yaw angle rate (r) and relative yaw angle (e_2). For example, the first rule of `fis2` describes that the steering angle u_2 is `negativeLow` (low negative value) when the yaw angle rate (r) and relative yaw angle (e_2) are both `negative`.
- Steering angles u_1 (output of `fis1`) and u_2 (output of `fis2`) have a negative correlation, that is, `fis3` output u_3 increases when u_1 increases, whereas u_3 decreases when u_2 increases. Hence, the lateral deviation and yaw angle have opposite effects on the steering angle.
- The rule base of `fis4` shows that the previous steering input u has insignificant effect on the steering angle calculation. The output u_4 of `fis4` uses similar linguistic variables as does the output of `fis3`.
- The measured disturbance d also has insignificant effect on the steering angle calculation since the output u_5 of `fis5` uses similar linguistic variables as does the output of `fis4`.


Hence, the rule bases of the FISs in the FIS tree describe the effects and relations between the input variables for steering calculation in the LKA system.

You can visualize each rule base using its control surface, which describes numerical mappings from the inputs to output according to the rule base.

```

figure
subplot(3,2,1)
gensurf(fisToutMF.FIS(1))
subplot(3,2,2)
gensurf(fisToutMF.FIS(2))
subplot(3,2,3)
gensurf(fisToutMF.FIS(3))
subplot(3,2,4)
gensurf(fisToutMF.FIS(4))
subplot(3,2,5)
gensurf(fisToutMF.FIS(5))

```




A fuzzy rule base provides linguistic relation between the inputs and output. The control surface augments this linguistic relation by adding numeric detail for input to output mapping.

Explain Run-Time Black-Box Predictions

The previous explanation of the black-box behavior describes the general relationships between the input observations and the resulting steering angle by interpreting the rule base of the fuzzy support system itself.

You can also use the support system to explain black-box outcomes generated in each control interval. The following diagram explains the parallel execution settings of the black-box model and the support system for run-time explanation of the black-box predictions.



The black-box model and the support system run in parallel and use the same input values (observations) for output prediction. The prediction from black-box model drives environment changes, while the support system only explains the black-box predictions. For this example, the fuzzy support system includes the following components in the explanation for each control interval.

- 1 Current simulation time
- 2 Current input values
- 3 Steering angle outputs generated by the DNN black-box model and fuzzy support system
- 4 Fuzzy rules having the maximum firing strength from each FIS of the FIS tree.

The output data format for each control interval is as follows.

```

===== Simulation time: <t> sec =====
inputs: [v r e1 e2 u d], outputs: [u*(DNN) u*(fuzzy)] rad
Max strength rules:
  fis1: <rule description>
  fis2: <rule description>
  fis3: <rule description>
  fis4: <rule description>
  fis5: <rule description>
    
```

The following simulation results explain the DNN model outputs in each control cycle using the fuzzy support system.

Initialize the vehicle state using the input from a test data point.

```
id = round(median(1:size(data.testInputData,1)));
x0 = data.testInputData(id,:);
```

Simulate the DNN and FIS with the same input data using the `compareDNNWithFIS` helper function.

```
[dnnOutputs,fisOutput] = compareDNNWithFIS(dnnLKA,fisTouMF,data,x0);
```

```
===== Simulation time: 0 sec =====
inputs: [0.0737824 -0.726656 -0.0161284 0.0484033 0.569496 -0.00256057],
outputs: [1.01041 1.0472] rad
Max strength rules:
  fis1: Vy==positive & e1==negative => u1=positive (1)
  fis2: r==positive & e2==positive => u2=positive (1)
  fis3: u1==positive & u2==negative => u3=positiveHigh (1)
  fis4: u3==positive & u==negative => u4=positive (1)
  fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 0.1 sec =====
inputs: [1.2579 -0.532934 1.33827 0.119282 1.01041 -0.00256057],
outputs: [-0.065464 -0.114224] rad
Max strength rules:
  fis1: Vy==positive & e1==negative => u1=positive (1)
  fis2: r==positive & e2==positive => u2=positive (1)
  fis3: u1==positive & u2==positive => u3=negative (1)
  fis4: u3==negative & u==negative => u4=negative (1)
  fis5: u4==negative & d==negative => u*=negative (1)
===== Simulation time: 0.2 sec =====
inputs: [-0.338464 -0.23482 0.745212 0.222974 -0.065464 -0.00256057],
outputs: [-0.933683 -0.982878] rad
Max strength rules:
  fis1: Vy==positive & e1==negative => u1=positive (1)
  fis2: r==positive & e2==positive => u2=positive (1)
  fis3: u1==positive & u2==positive => u3=negative (1)
  fis4: u3==negative & u==negative => u4=negative (1)
  fis5: u4==negative & d==negative => u*=negative (1)
===== Simulation time: 0.3 sec =====
inputs: [-1.86933 -0.0209625 -0.862648 0.212142 -0.933683 -0.00256057],
outputs: [-0.817988 -0.751812] rad
Max strength rules:
  fis1: Vy==negative & e1==negative => u1=positiveHigh (1)
  fis2: r==negative & e2==positive => u2=positiveHigh (1)
  fis3: u1==positive & u2==positive => u3=negative (1)
  fis4: u3==negative & u==negative => u4=negative (1)
  fis5: u4==negative & d==negative => u*=negative (1)
===== Simulation time: 0.4 sec =====
inputs: [-1.43016 0.0363023 -1.71046 0.0795595 -0.817988 -0.00256057],
outputs: [0.067486 0.285178] rad
Max strength rules:
  fis1: Vy==negative & e1==negative => u1=positiveHigh (1)
  fis2: r==negative & e2==positive => u2=positiveHigh (1)
  fis3: u1==positive & u2==negative => u3=positiveHigh (1)
  fis4: u3==positive & u==negative => u4=positive (1)
  fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 0.5 sec =====
```



```

inputs: [0.518155 0.0163838 -0.959078 -0.0526409 0.067486 -0.00256057],
outputs: [0.341617 0.307695] rad
Max strength rules:
  fis1: Vy==positive & e1==negative => u1=positive (1)
  fis2: r==negative & e2==negative => u2=negativeLow (1)
  fis3: u1==negative & u2==negative => u3=positive (1)
  fis4: u3==positive & u==negative => u4=positive (1)
  fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 0.6 sec =====
inputs: [1.43122 0.00176656 -0.024161 -0.0985401 0.341617 -0.00256057],
outputs: [0.2509 0.266469] rad
Max strength rules:
  fis1: Vy==positive & e1==negative => u1=positive (1)
  fis2: r==positive & e2==negative => u2=negative (1)
  fis3: u1==negative & u2==negative => u3=positive (1)
  fis4: u3==positive & u==negative => u4=positive (1)
  fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 0.7 sec =====
inputs: [1.16149 -0.000896715 0.439618 -0.075189 0.2509 -0.00256057],
outputs: [0.0708352 0.0913793] rad
Max strength rules:
  fis1: Vy==positive & e1==negative => u1=positive (1)
  fis2: r==positive & e2==negative => u2=negative (1)
  fis3: u1==negative & u2==negative => u3=positive (1)
  fis4: u3==negative & u==negative => u4=negative (1)
  fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 0.8 sec =====
inputs: [0.440392 -0.00281433 0.429965 -0.0306668 0.0708352 -0.00256057],
outputs: [-0.0181469 0.00702747] rad
Max strength rules:
  fis1: Vy==positive & e1==negative => u1=positive (1)
  fis2: r==positive & e2==negative => u2=negative (1)
  fis3: u1==positive & u2==negative => u3=positiveHigh (1)
  fis4: u3==negative & u==negative => u4=negative (1)
  fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 0.9 sec =====
inputs: [-0.0839108 -0.00710328 0.246287 0.00320763 -0.0181469 -0.00256057],
outputs: [-0.057111 -0.0431567] rad
Max strength rules:
  fis1: Vy==positive & e1==negative => u1=positive (1)
  fis2: r==positive & e2==negative => u2=negative (1)
  fis3: u1==positive & u2==negative => u3=positiveHigh (1)
  fis4: u3==negative & u==negative => u4=negative (1)
  fis5: u4==negative & d==negative => u*=negative (1)
===== Simulation time: 1 sec =====
inputs: [-0.302091 -0.0110731 0.0509454 0.0177286 -0.057111 -0.00256057],
outputs: [-0.0356868 -0.00903815] rad
Max strength rules:
  fis1: Vy==positive & e1==negative => u1=positive (1)
  fis2: r==positive & e2==positive => u2=positive (1)
  fis3: u1==positive & u2==negative => u3=positiveHigh (1)
  fis4: u3==negative & u==negative => u4=negative (1)
  fis5: u4==negative & d==negative => u*=negative (1)
===== Simulation time: 1.1 sec =====
inputs: [-0.258972 -0.012099 -0.0449731 0.0178176 -0.0356868 -0.00256057],
outputs: [-0.0338399 -0.00862586] rad
Max strength rules:
  fis1: Vy==positive & e1==negative => u1=positive (1)

```

```

    fis2: r==positive & e2==positive => u2=positive (1)
    fis3: u1==positive & u2==negative => u3=positiveHigh (1)
    fis4: u3==negative & u==negative => u4=negative (1)
    fis5: u4==negative & d==negative => u*=negative (1)
===== Simulation time: 1.2 sec =====
inputs: [-0.159426 -0.01097 -0.0910061 0.0109606 -0.0338399 -0.00256057],
outputs: [-0.0138318 0.000404072] rad
Max strength rules:
    fis1: Vy==positive & e1==negative => u1=positive (1)
    fis2: r==positive & e2==positive => u2=positive (1)
    fis3: u1==positive & u2==negative => u3=positiveHigh (1)
    fis4: u3==negative & u==negative => u4=negative (1)
    fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 1.3 sec =====
inputs: [-0.0423527 -0.0105425 -0.0811232 0.00251846 -0.0138318 -0.00256057],
outputs: [0.000331565 0.0269571] rad
Max strength rules:
    fis1: Vy==positive & e1==negative => u1=positive (1)
    fis2: r==positive & e2==negative => u2=negative (1)
    fis3: u1==positive & u2==negative => u3=positiveHigh (1)
    fis4: u3==negative & u==negative => u4=negative (1)
    fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 1.4 sec =====
inputs: [0.0361997 -0.0114349 -0.0471622 -0.00358271 0.000331565 -0.00256057],
outputs: [0.0304953 0.0473972] rad
Max strength rules:
    fis1: Vy==positive & e1==negative => u1=positive (1)
    fis2: r==positive & e2==negative => u2=negative (1)
    fis3: u1==positive & u2==negative => u3=positiveHigh (1)
    fis4: u3==negative & u==negative => u4=negative (1)
    fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 1.5 sec =====
inputs: [0.0930044 -0.0110261 0.0178849 -0.0045736 0.0304953 -0.00256057],
outputs: [0.00543895 0.0263826] rad
Max strength rules:
    fis1: Vy==positive & e1==negative => u1=positive (1)
    fis2: r==positive & e2==negative => u2=negative (1)
    fis3: u1==positive & u2==negative => u3=positiveHigh (1)
    fis4: u3==negative & u==negative => u4=negative (1)
    fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 1.6 sec =====
inputs: [0.0479661 -0.00916728 0.0247148 -0.00210616 0.00543895 -0.00256057],
outputs: [-0.00489231 0.013721] rad
Max strength rules:
    fis1: Vy==positive & e1==negative => u1=positive (1)
    fis2: r==positive & e2==negative => u2=negative (1)
    fis3: u1==positive & u2==negative => u3=positiveHigh (1)
    fis4: u3==negative & u==negative => u4=negative (1)
    fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 1.7 sec =====
inputs: [0.003968 -0.00833845 0.0109446 -7.63076e-05 -0.00489231 -0.00256057],
outputs: [-0.0103412 0.01063] rad
Max strength rules:
    fis1: Vy==positive & e1==negative => u1=positive (1)
    fis2: r==positive & e2==negative => u2=negative (1)
    fis3: u1==positive & u2==negative => u3=positiveHigh (1)
    fis4: u3==negative & u==negative => u4=negative (1)
    fis5: u4==positive & d==negative => u*=positive (1)

```

```

===== Simulation time: 1.8 sec =====
inputs: [-0.018166 -0.00892122 -0.00744728 0.000300259 -0.0103412 -0.00256057],
outputs: [-0.00482924 0.0185664] rad
Max strength rules:
  fis1: Vy==positive & e1==negative => u1=positive (1)
  fis2: r==positive & e2==negative => u2=negative (1)
  fis3: u1==positive & u2==negative => u3=positiveHigh (1)
  fis4: u3==negative & u==negative => u4=negative (1)
  fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 1.9 sec =====
inputs: [-0.0108874 -0.0104442 -0.0119736 -0.000442732 -0.00482924 -0.00256057],
outputs: [0.00649285 0.0270567] rad
Max strength rules:
  fis1: Vy==positive & e1==negative => u1=positive (1)
  fis2: r==positive & e2==negative => u2=negative (1)
  fis3: u1==positive & u2==negative => u3=positiveHigh (1)
  fis4: u3==negative & u==negative => u4=negative (1)
  fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 2 sec =====
inputs: [0.0102737 -0.0112775 0.00120234 -0.000692394 0.00649285 -0.00256057],
outputs: [0.00606821 0.023241] rad
Max strength rules:
  fis1: Vy==positive & e1==negative => u1=positive (1)
  fis2: r==positive & e2==negative => u2=negative (1)
  fis3: u1==positive & u2==negative => u3=positiveHigh (1)
  fis4: u3==negative & u==negative => u4=negative (1)
  fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 2.1 sec =====
inputs: [0.0123837 -0.0105726 0.00956563 0.000135922 0.00606821 -0.00256057],
outputs: [-0.00548619 0.0132276] rad
Max strength rules:
  fis1: Vy==positive & e1==negative => u1=positive (1)
  fis2: r==positive & e2==negative => u2=negative (1)
  fis3: u1==positive & u2==negative => u3=positiveHigh (1)
  fis4: u3==negative & u==negative => u4=negative (1)
  fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 2.2 sec =====
inputs: [-0.00638773 -0.00962137 -0.00104896 0.000793336 -0.00548619 -0.00256057],
outputs: [-0.0101492 0.0127081] rad
Max strength rules:
  fis1: Vy==positive & e1==negative => u1=positive (1)
  fis2: r==positive & e2==negative => u2=negative (1)
  fis3: u1==positive & u2==negative => u3=positiveHigh (1)
  fis4: u3==negative & u==negative => u4=negative (1)
  fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 2.3 sec =====
inputs: [-0.0150607 -0.00993627 -0.0145728 0.000219597 -0.0101492 -0.00256057],
outputs: [-0.000622757 0.0224694] rad
Max strength rules:
  fis1: Vy==positive & e1==negative => u1=positive (1)
  fis2: r==positive & e2==negative => u2=negative (1)
  fis3: u1==positive & u2==negative => u3=positiveHigh (1)
  fis4: u3==negative & u==negative => u4=negative (1)
  fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 2.4 sec =====
inputs: [0.00129177 -0.0109741 -0.0100013 -0.000752015 -0.000622757 -0.00256057],
outputs: [0.00826707 0.0272876] rad
Max strength rules:

```


```

    fis1: Vy==positive & e1==negative => u1=positive (1)
    fis2: r==positive & e2==negative => u2=negative (1)
    fis3: u1==positive & u2==negative => u3=positiveHigh (1)
    fis4: u3==negative & u==negative => u4=negative (1)
    fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 2.5 sec =====
inputs: [0.0180957 -0.0110403 0.00564726 -0.000665081 0.00826707 -0.00256057],
outputs: [0.00268279 0.0195868] rad
Max strength rules:
    fis1: Vy==positive & e1==negative => u1=positive (1)
    fis2: r==positive & e2==negative => u2=negative (1)
    fis3: u1==positive & u2==negative => u3=positiveHigh (1)
    fis4: u3==negative & u==negative => u4=negative (1)
    fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 2.6 sec =====
inputs: [0.00964111 -0.00996293 0.00814168 0.000300964 0.00268279 -0.00256057],
outputs: [-0.00864593 0.0113771] rad
Max strength rules:
    fis1: Vy==positive & e1==negative => u1=positive (1)
    fis2: r==positive & e2==negative => u2=negative (1)
    fis3: u1==positive & u2==negative => u3=positiveHigh (1)
    fis4: u3==negative & u==negative => u4=negative (1)
    fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 2.7 sec =====
inputs: [-0.010699 -0.00937352 -0.00624496 0.000612816 -0.00864593 -0.00256057],
outputs: [-0.00803829 0.0154325] rad
Max strength rules:
    fis1: Vy==positive & e1==negative => u1=positive (1)
    fis2: r==positive & e2==negative => u2=negative (1)
    fis3: u1==positive & u2==negative => u3=positiveHigh (1)
    fis4: u3==negative & u==negative => u4=negative (1)
    fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 2.8 sec =====
inputs: [-0.0111992 -0.0101628 -0.0149542 -0.0002283 -0.00803829 -0.00256057],
outputs: [0.00356172 0.0254184] rad
Max strength rules:
    fis1: Vy==positive & e1==negative => u1=positive (1)
    fis2: r==positive & e2==negative => u2=negative (1)
    fis3: u1==positive & u2==negative => u3=positiveHigh (1)
    fis4: u3==negative & u==negative => u4=negative (1)
    fis5: u4==positive & d==negative => u*=positive (1)
===== Simulation time: 2.9 sec =====
inputs: [0.00883607 -0.0110872 -0.00433228 -0.000913514 0.00356172 -0.00256057],
outputs: [0.00806086 0.0257673] rad
Max strength rules:
    fis1: Vy==positive & e1==negative => u1=positive (1)
    fis2: r==positive & e2==negative => u2=negative (1)
    fis3: u1==positive & u2==negative => u3=positiveHigh (1)
    fis4: u3==negative & u==negative => u4=negative (1)
    fis5: u4==positive & d==negative => u*=positive (1)

```

Plot the DNN and FIS outputs.

```
plotValidationResults(data.Ts,dnnOutputs,fisOutput)
```




As expected, the fuzzy support system produces similar steering angle outputs as compared to the DNN black-box model.

Explanation Using Fuzzy Rule Inference

You can further explore the decision-making process of a FIS in the tree using its rule inference viewer. For example, the following simulation shows rule inference process of `fis1` of the FIS tree.

```
fisIndex = 1;  
showRuleInference(data, fisToutMF, fisIndex, x0)
```




The left plot shows the output pattern of `fis1` as compared to the overall FIS tree output. The right plot shows individual rule activations of `fis1` in each control cycle.

FIS Tree Data Propagation

Finally, you can also visualize how each FIS contributes to the decision-making process for a given set of input values. The following example shows output propagation in the FIS tree for a test input vector.

```
[~,~,fisIns,fisOuts] = evaluateFISTree(fisToutMF,[x0(1) x0(3) x0(2) x0(4:6)]);
fisTwithIOValues = updateLabelsWithIOValues(fisToutMF,fisIns,fisOuts);

showFISTree(fisTwithIOValues,0.85)
```



For this combination of input values, the output of `fis1` dominates over the `fis2` output, which indicates that lateral displacement and its rate contribute more to the overall output value.


Conclusion

You can further improve the performance of the support fuzzy system by using:


- Additional input MFs
- Continuous MFs for smooth variations in outputs
- More training data, and
- Different configurations of the FIS tree, as shown in the following figure

`showOtherBlackBoxFISTrees(data)`

Example 1



Example 2



Different tuning methods with different random number generation seeds may also improve the optimization of the support system.

You can also intuitively update each individual FIS rule base to check possible variations in output generation to further improve the performance of the support system.

Helper Functions

```
function fis = constructFIS(name,numMFs,in1range,in2range,outrange,in1,in2,out)
% Construct a Sugeno FIS.
```

```

fis = sugfis('Name',name);
numOutputMFs = numMFs^2;
fis = addInput(fis,in1range,'Name',in1,'NumMFs',numMFs);
fis = addInput(fis,in2range,'Name',in2,'NumMFs',numMFs);
for ct = 1:2
    fis.Inputs(ct).MembershipFunctions(1).Type = 'linzmf';
    fis.Inputs(ct).MembershipFunctions(end).Type = 'linsmf';
    numMFs = length(fis.Inputs(ct).MembershipFunctions);
end
fis = addOutput(fis,outrange,'Name',out,'NumMFs',numOutputMFs);
range = 1:numMFs;
[in1,in2] = ndgrid(range,range);
rules = [in1(:) in2(:) ones(numOutputMFs,3)];
fis = addRule(fis,rules);
end
```

```

function [rms,yFIS] = calculateRMS(fis,x,y)
% Evaluate the FIS using the specified input data and calculate the RMS error
% the simulated and reference outputs.
```



```

options = evalfisOptions;
options.EmptyOutputFuzzySetMessage = 'none';
options.NoRuleFiredMessage = 'none';
options.OutOfRangeInputValueMessage = 'none';

yFIS = evalfis(fis,x,options);
e = yFIS - y;
rms = sqrt(mean(e.*e));
end

function showRules(fisT)
% Display rule bases of the FISs in a FIS tree as tables.

fis1Rules = [fisT.FIS(1).Rules.Description]';
fis2Rules = [fisT.FIS(2).Rules.Description]';
fis3Rules = [fisT.FIS(3).Rules.Description]';
fis4Rules = [fisT.FIS(4).Rules.Description]';
fis5Rules = [fisT.FIS(5).Rules.Description]';

disp(table(fis1Rules,fis2Rules))
disp(table(fis3Rules,fis4Rules))
disp(table(fis5Rules))
end

function [uHistoryDNN,uHistoryFIS] = compareDNNwithFIS(dnnLKA,fisToutMF,data,x0)
% Compares DNN and FIS tree model.

xHistoryDNN = repmat(x0(1:4),data.Tsteps+1,1);
uHistoryDNN = zeros(data.Tsteps,1);
uHistoryFIS = zeros(data.Tsteps,1);

lastMV = x0(5);
d = x0(6);
for k = 1:data.Tsteps
% Obtain plant output measurements, which correspond to the plant outputs.
xk = xHistoryDNN(k,:);
% Predict the next move using the trained deep neural network.
in = [xk',lastMV,d];
ukDNN = predict(dnnLKA,in);
% Predict the next move using the trained fuzzy system.
tmp = in(2); in(2) = in(3); in(3) = tmp; % config 1
[ukFIS,maxRules] = evaluateFISTree(fisToutMF,in);
% Store the control action and update the last MV for the next step.
uHistoryDNN(k,:) = ukDNN;
uHistoryFIS(k,:) = ukFIS;
lastMV = ukDNN;
% Update the state using the control action.
xHistoryDNN(k+1,:) = (data.A*xk + data.B*[ukDNN;d]);

% Explanations/diagnostics
fprintf('\n===== Simulation time: %g sec =====',...
(k-1)*data.Ts);
fprintf('\ninputs: [%g %g %g %g %g %g], \noutputs: [%g %g] rad', ...
in(1),in(2),in(3),in(4),in(5),in(6),ukDNN,ukFIS);
fprintf('\nMax strength rules:');
fprintf('\n\tfis1: %s\n\tfis2: %s\n\tfis3: %s\n\tfis4: %s\n\tfis5: %s', ...
maxRules(1),maxRules(2),maxRules(3),maxRules(4),maxRules(5));
end

```

```

end

function [y,maxRules,fisIns,fisOuts] = evaluateFISTree(fisT,x)
% Evaluates FIS tree with the specified input values.

options = evalfisOptions;
options.OutOfRangeInputValueMessage = 'none';
options.NoRuleFiredMessage = 'none';
options.EmptyOutputFuzzySetMessage = 'none';

numFIS = numel(fisT.FIS);
fisIns = zeros(numFIS,2);

fisIns(1,:) = x(1:2);
[y1,~,~,~,rfs1] = evalfis(fisT.FIS(1),x(1:2),options);
fisIns(2,:) = x(3:4);
[y2,~,~,~,rfs2] = evalfis(fisT.FIS(2),x(3:4),options);
fisIns(3,:) = [y1 y2];
[y3,~,~,~,rfs3] = evalfis(fisT.FIS(3),[y1 y2],options);
fisIns(4,:) = [y3 x(5)];
[y4,~,~,~,rfs4] = evalfis(fisT.FIS(4),[y3 x(5)],options);
fisIns(5,:) = [y4 x(6)];
[y,~,~,~,rfs5] = evalfis(fisT.FIS(5),[y4 x(6)],options);

fisOuts = [y1 y2 y3 y4 y];

[~,id1] = sort(rfs1,'descend');
[~,id2] = sort(rfs2,'descend');
[~,id3] = sort(rfs3,'descend');
[~,id4] = sort(rfs4,'descend');
[~,id5] = sort(rfs5,'descend');

maxRules = [...
    fisT.FIS(1).Rules(id1(1)).Description; ...
    fisT.FIS(2).Rules(id2(1)).Description; ...
    fisT.FIS(3).Rules(id3(1)).Description; ...
    fisT.FIS(4).Rules(id4(1)).Description; ...
    fisT.FIS(5).Rules(id5(1)).Description ...
    ];
end

function plotValidationResults(Ts,uDNN,uFIS)
% Plot validation results of the DNN and FIS tree model.
figure

% Plot output steering angles of DNN and FIS.
Tu = ((0:(size(uDNN,1)-1)*Ts)');
stairs(Tu,uDNN);
title('DNN and FIS output comparison')
xlabel('Time (s)')
ylabel('Steering angle (rad)')
axis([0 Tu(end) -1.1 1.1]);
hold on
stairs(Tu,uFIS);
legend('DNN','FIS')
grid on;
hold off

```

```
pause(0.1)  
end
```

See Also

[tunefis](#) | [getTunableSettings](#) | [fistree](#)

More About

- “Tuning Fuzzy Inference Systems” on page 3-2
- “Fuzzy Trees” on page 2-52
- “Explainable Fuzzy Support System for Black-Box Model of Robot Obstacle Avoidance” on page 3-154

Explainable Fuzzy Support System for Black-Box Model of Robot Obstacle Avoidance

This example shows how to develop a support fuzzy inference system to explain the behavior of a black-box model when the original data used to train the black-box model is not available.


Using nondeterministic machine learning methods, such as reinforcement learning, you can design a black-box model to estimate the input-output mapping for a given set of experimental or simulation data. However, the input-output relationship defined by such a black-box model is difficult to understand.

In general, users are unable to explain the causal relations from the inputs to the outputs. Also, they are unable to change the system behavior using the implicit input-output models. To resolve these problems, a common approach is to create a transparent support system for the black-box model. The goal of such a support system is to help users understand and explain the input-output relationships developed in a black box model.

A fuzzy inference system (FIS) is a transparent model that represents system knowledge using an explainable rule base. Since the rule base of a fuzzy system is easier for a user to intuitively understand, a FIS is often used as a support system to explain an existing black-box model.

The following figure shows the general steps for developing a fuzzy support system from an existing black-box model when the original training data for the black-box model is not available.


- 1 Generate black-box model outputs for a given set of test data.
- 2 Tune a FIS using the test input data and generated output data.
- 3 Finally, compare the performance of the models and explain the black-box predictions using the FIS.



In general, you can use a fuzzy support system to explain different types of black-box models. For this example, the black-box model is implemented using a reinforcement learning (RL) agent, which requires Reinforcement Learning Toolbox™ software.

Navigation Environment

The RL agent in this example is trained to navigate a robot in a simulation environment while avoiding obstacles. The navigation environment is described in “Tune Fuzzy Robot Obstacle Avoidance System Using Custom Cost Function” on page 3-71.



The environment describes a navigation task to reach a specified target while avoiding obstacles. The direction to the target is represented as a unit force vector (\vec{F}_t) directed from the robot to a target location. The obstacle avoidance direction is represented by a unit force vector (\vec{F}_o) directed towards the robot from the closest obstacle location. The robot, target, and obstacle are shown as circles with 0.5 m radius in the 25 m x 25 m simulation environment. The navigation task is to combine the force vectors such that the direction θ of the resultant force vector \vec{F} provides a collision-free direction for the robot.

$$\vec{F} = w\vec{F}_o + (1 - w)\vec{F}_t, \text{ where } 0 \leq w \leq 1$$

$$\theta = \angle \vec{F}$$

The weight w of the force vector \vec{F}_o is calculated using function f_w .

$$w = f_w(\alpha, \theta_{t,o})$$

Here:

- $\alpha = \frac{d_o}{d_t}$ is the ratio of the robot-to-obstacle distance (d_o) and the robot-to-target-distance (d_t)
- $\theta_{t,o}$ is the absolute difference between the target and obstacle directions with respect to the robot

The RL agent learns a policy to model f_w for collision-free robot navigation in the environment using $(\alpha, \theta_{t,o})$ as the observation and w as the action.

Policy Simulation

To simulate the learned policy, first load the trained RL agent.


```
rlmodel = load("rlNavModel.mat");  
trainedAgent = rlmodel.trainedAgent;
```

Create the simulation environment using an RL environment object as defined in the `NavigationEnvironment.m` helper file. This environment definition also includes several helper functions used in this example.

```
env = NavigationEnvironment;
```

Simulate the agent in the navigation environment.

```
sim(trainedAgent,env)
```



The trained RL agent successfully avoids obstacles using a learned policy.

However, the agent does not provide an explanation about how it avoids the obstacle. The actor of the agent uses a deep neural network (DNN) model, which encapsulates the navigation policy in terms of hidden units and their associated parameters. As an example, you can directly simulate the actor of the agent to generate an action for a specific observation as follows.

```
alpha = 0.1;
theta = 0;
obstacleWeight = trainedAgent.getAction([alpha;theta])

obstacleWeight = 1x1 cell array
    {[0.9253]}
```


The actor produces a high weight for obstacle avoidance. However, it does not provide any tools to explain how the knowledge is represented in the model and how it has been used to generate the action in this case.

Generate Test Data

To explain the agent actions, you can develop a fuzzy support system using a data-driven approach. To do so, you must first generate input-output training data using different test cases, where each case represents different direction of the robot. For n test cases, the robot direction is specified as $\pm \frac{2\pi}{n}$ rad. In each case, the target, obstacle, and the robot are located along the same line. However, their relative distances are varied randomly.

Generate four test cases using the `createTestCases` helper function. You can visualize the test cases using the `showTestCases` helper function.

```
numTestCases = 4;
rng("default")
testCases = createTestCases(env,numTestCases);
showTestCases(env,testCases)
```



Use the test cases to generate input-output training data for the fuzzy system using the `generateData` helper function.

```
[X,Y] = generateData(env,trainedAgent,testCases);
```




Create and Tune Support System

To define the fuzzy support system, you must create and tune a FIS.

Create Initial FIS

Create a Mamdani fuzzy inference system.

```
fisin = mamfis;
```

Add two input variables for the observations. Each input includes two linear saturation membership functions (MFs).

```
numMFs = 2;
% Input 1
fisin = addInput(fisin,[0 2],"Name","alpha","NumMFs",numMFs);
fisin.Inputs(1).MembershipFunctions(1).Type = "linzmf";
fisin.Inputs(1).MembershipFunctions(end).Type = "linsmf";

% Input 2
fisin = addInput(fisin,[0 pi/2],"Name","theta_t_o","NumMFs",numMFs);
fisin.Inputs(2).MembershipFunctions(1).Type = "linzmf";
fisin.Inputs(2).MembershipFunctions(end).Type = "linsmf";
```

Add an output variable for the action, which represents the weight (priority) of obstacle avoidance. Add output MFs for all possible combinations of input MFs.


```
numOutMFs = numMFs^2;
fisin = addOutput(fisin,[0 1],"Name","w","NumMFs",numOutMFs);
```

Next, add default rules for all combinations of input MFs. The default rules always produce a low weight for obstacle avoidance.

```
[in1,in2] = ndgrid(1:numMFs,1:numMFs);
rules = [in1(:) in2(:) ones(numOutMFs,3)];
fisin = addRule(fisin,rules);
```

Show the initial FIS.

```
figure
plotfis(fisin)
```



System fis: 2 inputs, 1 outputs, 4 rules

Tune FIS

To train the FIS, use the following two stages.

- Learn the rule base to establish the input-output relationships.
- Tune the membership function parameters for the input and output variables.

To tune the rules, first obtain the rule parameter settings from the FIS.

```
[~,~,rule] = getTunableSettings(fisin);
```

Since you have a rule for each possible input combination, configure the training settings to keep the rule antecedents fixed. As a result, tuning will only modify the rule consequents.

```

for ct = 1:length(rule)
    rule(ct).Antecedent.Free = 0;
end
    
```

Create an option set for tuning and specify `particleswarm` as the tuning method. Set maximum number of tuning iterations to 50.

```

options = tunefisOptions("Method","particleswarm");
options.MethodOptions.MaxIterations = 50;
    
```

Tuning is a time-consuming process. For this example, load a pretrained FIS by setting `runtunefis` to `false`. To tune the FIS yourself instead, set `runtunefis` to `true`.

```

runtunefis = false;
    
```

Tune the fuzzy rules. For reproducibility, reset the random number generator using the default seed.

```

if runtunefis
    rng("default")
    fisR = tunefis(fisin,rule,X,Y,options);
else
    data = load("flNavModel.mat");
    fisR = data.fisR;
end
    
```

Display the tuned rules.

```

disp([fisR.Rules.Description]')

"alpha==mf1 & theta_t_o==mf1 => w=mf2 (1)"
"alpha==mf2 & theta_t_o==mf1 => w=mf1 (1)"
"alpha==mf1 & theta_t_o==mf2 => w=mf1 (1)"
"alpha==mf2 & theta_t_o==mf2 => w=mf1 (1)"
    
```

Output membership functions 3 and 4 are not used in the rule base. Remove these membership functions from the output variable.

```

fisR.Outputs(1).MembershipFunctions(3:4) = [];
    
```

Next, tune the input and output MF parameters. To do so, first obtain the corresponding tunable settings from the FIS.

```

[in,out] = getTunableSettings(fisR);
    
```

For this tuning step, use the `patternsearch` algorithm fine tuning of the MF parameters and set maximum number of iterations number to 100.

```

options.Method = "patternsearch";
options.MethodOptions.MaxIterations = 100;
    
```


Tune the MF parameters.

```

if runtunefis
    rng("default")
    fisMF = tunefis(fisR,[in;out],X,Y,options);
else
    fisMF = data.fisMF;
end
    
```

Show the tuned fuzzy system.

```
fisout = fisMF;  
figure  
plotfis(fisout)
```



System fis: 2 inputs, 1 outputs, 4 rules

Simulate Fuzzy System

Validate the tuned FIS for the test cases using the `simTestCasesWithFIS` helper function.

```
simTestCasesWithFIS(env, fisout, testCases)
```



The tuned fuzzy system generates similar reward values for the test cases as compared to the RL agent.

Explain Black-Box Model

With a trained support system, you can now explain the behavior of the black-box model.

Explainable Rule Base with Meaningful MF Names

For interpretability, first, specify names of the MFs for each input and output variable as low and high.

```

fisout.Inputs(1).MembershipFunctions(1).Name = "low";
fisout.Inputs(1).MembershipFunctions(2).Name = "high";
fisout.Inputs(2).MembershipFunctions(1).Name = "low";
fisout.Inputs(2).MembershipFunctions(2).Name = "high";
fisout.Outputs(1).MembershipFunctions(1).Name = "low";
fisout.Outputs(1).MembershipFunctions(2).Name = "high";
    
```

View the tuned rules with the updated names.

```

disp([fisout.Rules.Description]')

"alpha==low & theta_t_o==low => w=high (1)"
"alpha==high & theta_t_o==low => w=low (1)"
"alpha==low & theta_t_o==high => w=low (1)"
"alpha==high & theta_t_o==high => w=low (1)"
    
```

Using these rules, you can explain the behavior of the RL agent.


- In the first rule, when α is low (the obstacle is located closer to the robot as compared to the target) and $\theta_{t,o}$ is low (the obstacle and target are located in the same direction), the robot should actively avoid the obstacle. In this case, collision avoidance has a higher priority than reaching the target.
- In the second rule, when α is high (both the obstacle and the target are located away from the robot) and $\theta_{t,o}$ is low (the obstacle and target are located in the same direction), the robot can still move towards the target to optimize the travel distance. In this case, reaching the target has a higher priority than collision avoidance.
- In the third and fourth rules, $\theta_{t,o}$ is high (the obstacle and target are located in different directions). In this case, the robot can always safely navigate towards the target. Therefore, reaching the target has a higher priority than collision avoidance.

Overall, the black-box action (collision avoidance weight) is explainable using the rule base of the fuzzy support system.

Visualization of Observation-to-Action Mapping

The control surface of the fuzzy system describes observations (input) to actions (output) mapping according to the rule base.


figure
gensurf(fisMF)



The fuzzy rule base provides a linguistic relation between the observations and actions; whereas the control surface augments this linguistic relation by adding numeric details for observation-to-action mapping.

Explanation of Runtime Action Selection

You can also use the support system to explain each black-box action generated in a control cycle. The following diagram explains the parallel execution settings of both the black-box model and the support system for run-time explanation of an action.



The black-box model and the support system run in parallel and use the same environment observations. The black-box model drives environment changes. The support system observes the environment and explains the black-box action. For this example, the support system explanation includes the following information.

- 1 Index of the control cycle
- 2 Current observation
- 3 Action (obstacle weight) generated by the black-box model and the fuzzy support system
- 4 Fuzzy rule that is most suitable based on the current observation

The output data format for each control interval is as follows.

```

===== Control cycle: 1 =====
Observations = [0.466667 0], agent output (weight) = 0.582038, FIS output (weight) = 0.545197
Max strength rule: alpha==low & theta_t_o==low => w=high (1)
    
```

Simulate the agent and FIS using the `compareAgentWithFIS` helper function. The results show explanations for each action and the overall navigation trajectory using the black-box model.

```

setDefaultPositions(env);
[agentActions,fisActions] = compareAgentWithFIS(env,trainedAgent,fisout);
    
```

```
===== Control cycle: 1 =====
Observations = [0.8 0], agent output (weight) = 0.000371873, FIS output (weight) = 0.0097047
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 2 =====
Observations = [0.794872 0], agent output (weight) = 0.000371873, FIS output (weight) = 0.0097411
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 3 =====
Observations = [0.789474 0], agent output (weight) = 0.000409514, FIS output (weight) = 0.0097804
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 4 =====
Observations = [0.783784 0], agent output (weight) = 0.000453234, FIS output (weight) = 0.0098222
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 5 =====
Observations = [0.777778 0], agent output (weight) = 0.000504375, FIS output (weight) = 0.0098674
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 6 =====
Observations = [0.771429 0], agent output (weight) = 0.000564635, FIS output (weight) = 0.0099155
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 7 =====
Observations = [0.764706 0], agent output (weight) = 0.00063616, FIS output (weight) = 0.0099685
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 8 =====
Observations = [0.757576 0], agent output (weight) = 0.000721812, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 9 =====
Observations = [0.75 0], agent output (weight) = 0.000842512, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 10 =====
Observations = [0.741935 0], agent output (weight) = 0.000993103, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 11 =====
Observations = [0.733333 0], agent output (weight) = 0.00118306, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 12 =====
Observations = [0.724138 0], agent output (weight) = 0.00142586, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 13 =====
Observations = [0.714286 0], agent output (weight) = 0.00174063, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 14 =====
Observations = [0.703704 0], agent output (weight) = 0.00215521, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 15 =====
Observations = [0.692308 0], agent output (weight) = 0.00271079, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 16 =====
Observations = [0.68 0], agent output (weight) = 0.00346974, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 17 =====
Observations = [0.666667 0], agent output (weight) = 0.00452864, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 18 =====
Observations = [0.652174 0], agent output (weight) = 0.00657335, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 19 =====
Observations = [0.636364 0], agent output (weight) = 0.00989613, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 20 =====
```



```


Observations = [0.619048 0], agent output (weight) = 0.0154329, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 21 =====
Observations = [0.6 0], agent output (weight) = 0.0238907, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 22 =====
Observations = [0.578947 0], agent output (weight) = 0.0415951, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 23 =====
Observations = [0.555556 0], agent output (weight) = 0.0757059, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 24 =====
Observations = [0.529412 0], agent output (weight) = 0.158672, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 25 =====
Observations = [0.5 0], agent output (weight) = 0.325787, FIS output (weight) = 0.01
Max strength rule: alpha==high & theta_t_o==low => w=low (1)
===== Control cycle: 26 =====
Observations = [0.466667 0], agent output (weight) = 0.582038, FIS output (weight) = 0.545197
Max strength rule: alpha==low & theta_t_o==low => w=high (1)
===== Control cycle: 27 =====
Observations = [0.428571 0], agent output (weight) = 0.770591, FIS output (weight) = 0.703252
Max strength rule: alpha==low & theta_t_o==low => w=high (1)
===== Control cycle: 28 =====
Observations = [0.401145 0.0796649], agent output (weight) = 0.81328, FIS output (weight) = 0.76
Max strength rule: alpha==low & theta_t_o==low => w=high (1)
===== Control cycle: 29 =====
Observations = [0.414964 0.184271], agent output (weight) = 0.729063, FIS output (weight) = 0.73
Max strength rule: alpha==low & theta_t_o==low => w=high (1)
===== Control cycle: 30 =====
Observations = [0.447487 0.249775], agent output (weight) = 0.381589, FIS output (weight) = 0.5
Max strength rule: alpha==low & theta_t_o==low => w=high (1)
===== Control cycle: 31 =====
Observations = [0.459347 0.339489], agent output (weight) = 0.0742273, FIS output (weight) = 0.0
Max strength rule: alpha==low & theta_t_o==high => w=low (1)
===== Control cycle: 32 =====
Observations = [0.446 0.436475], agent output (weight) = 0.00935188, FIS output (weight) = 0.01
Max strength rule: alpha==low & theta_t_o==high => w=low (1)
===== Control cycle: 33 =====
Observations = [0.40865 0.524433], agent output (weight) = 0.00226036, FIS output (weight) = 0.0
Max strength rule: alpha==low & theta_t_o==high => w=low (1)
===== Control cycle: 34 =====
Observations = [0.369292 0.650354], agent output (weight) = 0.00163391, FIS output (weight) = 0.0
Max strength rule: alpha==low & theta_t_o==high => w=low (1)
===== Control cycle: 35 =====
Observations = [0.331602 0.837792], agent output (weight) = 0.000674069, FIS output (weight) = 0
Max strength rule: alpha==low & theta_t_o==high => w=low (1)
===== Control cycle: 36 =====
Observations = [0.305187 1.11815], agent output (weight) = 0.00017646, FIS output (weight) = 0.0
Max strength rule: alpha==low & theta_t_o==high => w=low (1)
===== Control cycle: 37 =====
Observations = [0.310447 1.49858], agent output (weight) = 3.00407e-05, FIS output (weight) = 0.0
Max strength rule: alpha==low & theta_t_o==high => w=low (1)
===== Control cycle: 38 =====
Observations = [0.37532 1.9], agent output (weight) = 8.04663e-07, FIS output (weight) = 0.00961
Max strength rule: alpha==low & theta_t_o==high => w=low (1)
===== Control cycle: 39 =====
Observations = [0.521888 2.21788], agent output (weight) = 0, FIS output (weight) = 0.01

```

```

Max strength rule: alpha==high & theta_t_o==high => w=low (1)
===== Control cycle: 40 =====
Observations = [0.774188 2.4342], agent output (weight) = 0, FIS output (weight) = 0.00989476
Max strength rule: alpha==high & theta_t_o==high => w=low (1)
===== Control cycle: 41 =====
Observations = [1.19014 2.57834], agent output (weight) = 0, FIS output (weight) = 0.00796472
Max strength rule: alpha==high & theta_t_o==high => w=low (1)
===== Control cycle: 42 =====
Observations = [1.92626 2.67745], agent output (weight) = 0, FIS output (weight) = 0.00625
Max strength rule: alpha==high & theta_t_o==high => w=low (1)
===== Control cycle: 43 =====
Observations = [3.50085 2.7485], agent output (weight) = 0, FIS output (weight) = 0.00625
Max strength rule: alpha==high & theta_t_o==high => w=low (1)

```




The support system produces similar obstacle weights compared to the black-box model. This result is more evident from the following figure, which shows the difference between agent and fuzzy support system actions for the same observations.

```

figure
plot(agentActions)
hold on
plot(fisActions)
hold off
xlabel("Decision cycle")
ylabel("Weight for obstacle avoidance")
legend(["Agent actions" "FIS actions"])

```




The fuzzy support system generates similar actions. However, it requires further optimizations to better match the agent actions.

Explanation Using Fuzzy Rule Inference

You can further explore the decision-making process of a FIS using its rule inference viewer. To do so, use the `simFISWithInferenceViewer` helper function. In this case, the fuzzy system drives the changes in the environment.

```
simFISWithInferenceViewer(env, fisout)
```



In each step, the rule inference process shows the fuzzification of the observation values, calculation of rule activation strengths, individual rule contributions in the output, and calculation of the final action value. Therefore, it shows an explainable visualization of the fuzzy rule applicability based on each observation of the environment.

Conclusion

You can further improve the performance of the fuzzy support system by using:

- More test cases
- Additional input MFs
- Continuous MFs for smooth variations in the actions.

You can also intuitively update the fuzzy rule base to check possible variations of the current policy of the black-box model and, if possible, integrate the desired variations with existing black-box model.

See Also

tunefis | getTunableSettings

More About

- “Tuning Fuzzy Inference Systems” on page 3-2
- “Explain Black-Box Model Using Fuzzy Support System” on page 3-131

Neuro-Adaptive Learning and ANFIS

Suppose that you want to apply fuzzy inference to a system for which you already have a collection of input/output data that you would like to use for modeling, model-following, or some similar scenario. Also, assume that you do not necessarily have a predetermined model structure based on the characteristics of variables in your system. In some modeling situations, discerning membership functions parameters by looking at data can be difficult or impossible. In these cases, rather than choosing the parameters associated with a given membership function arbitrarily, you can tailor the membership function parameters to the input/output data. Using Fuzzy Logic Toolbox software, you can tune Sugeno fuzzy inference systems using neuro-adaptive learning techniques similar to those used for training neural networks.

Fuzzy Logic Toolbox software provides a command-line function (`anfis`) and an interactive app (**Neuro-Fuzzy Designer**) for training an adaptive neuro-fuzzy inference system (ANFIS).

FIS Structure

Using ANFIS training methods, you can train Sugeno systems with the following properties:

- Single output
- Weighted average defuzzification
- First or zeroth order system; that is, all output membership functions must be the same type, either 'linear' or 'constant'.
- No rule sharing. Different rules cannot use the same output membership function; that is, the number of output membership functions must equal the number of rules.
- Unity weight for each rule.
- No custom membership functions or defuzzification methods.

To create such a fuzzy system in the MATLAB workspace, you can:

- Use the `genfis` function. When using this method, you can create your system using either grid partitioning or subtractive clustering. Grid partitioning can produce a large number of rules when the number of inputs reaches four or five. To reduce the number of rules, consider using the subtractive clustering method.
- Use the **Fuzzy Logic Designer** app, and export the FIS to the MATLAB workspace.
- Use the `sugfis` function.
- Load a system from a file using the `readfis` function.

When training your system using the `anfis` function, specify the initial structure by creating an `anfisOptions` option set and setting the `InitialFIS` property. If you do not specify this property, the `anfis` function derives the FIS structure using grid partitioning.

When using **Neuro-Fuzzy Designer**, in the **Generate FIS** section, you can create your FIS by:

- Loading from a file (select **Load from file**)
- Loading from the MATLAB workspace (select **Load from worksp**)
- Using grid partitioning (select **Grid partition**)
- Using subtractive clustering (select **Sub. clustering**)

Training Data

To train a fuzzy system using neuro-adaptive methods, you must collect input/output training data using experiments or simulations of the system you want to model. In general, ANFIS training works well if the training data is fully representative of the features of the data that the trained FIS is intended to model.

To specify your training data, you can:

- Create an array in the MATLAB workspace. Each row contains a data point, with the final column containing the output value and the remaining columns containing input values. You can then pass this data to the `trainingData` input argument of the `anfis` function or load it into the **Neuro-Fuzzy Designer** app.
- Load the data from a `.dat` file. Each line of the file contains a data point with values separated by white space. The final value on each line is the output, and the remaining values are the inputs.

When using the `anfis` function, create or load the input data and pass it to the `trainingData` input argument.

When using **Neuro-Fuzzy Designer**, in the **Load data** section, select **Training**, and then:

- To load data from a file, select **file**.
- To load data from the MATLAB workspace, select **worksp**.

Training Options

Both `anfis` and **Neuro-Fuzzy Designer** allow you to adjust the optimization method, number of training epochs, and training error goal. However, `anfis` provides additional training options to control the training step size.

Option	<code>anfisOptions</code> Property	Neuro-Fuzzy Designer Setting
Optimization Method	<code>OptimizationMethod</code>	In the Train FIS section, specify Optim. Method .
Number of training epochs	<code>EpochNumber</code>	In the Train FIS section, specify Epochs .
Training error goal	<code>ErrorGoal</code>	In the Train FIS section, specify Error Tolerance .
Initial step size	<code>InitialStepSize</code>	Not available
Step-size decrease rate	<code>StepSizeDecreaseRate</code>	
Step-size increase rate	<code>StepSizeIncreaseRate</code>	

Optimization Method

To train a fuzzy system using ANFIS, the Fuzzy Logic Toolbox software uses a back-propagation algorithm either alone or in combination with a least-squares algorithm. This training process tunes the membership function parameters of a FIS such that the system models your input/output data.

The following table shows the two methods that both `anfis` and **Neuro-Fuzzy Designer** use for updating membership function parameters.

Optimization Method	anfisOptions Setting	Neuro-Fuzzy Designer Setting
Backpropagation for all parameters (a steepest-descent method)	OptimizationMethod = 'backpropagation'	In the Train FIS section, under Optim. Method , select backpropa.
Hybrid method consisting of backpropagation for the parameters associated with the input membership functions, and least squares estimation for the parameters associated with the output membership functions	OptimizationMethod = 'hybrid'	In the Train FIS section, under Optim. Method , select hybrid.

Step Size

When training using the `anfis` function, you can adjust the training step size options. During training, the software updates the step-size according to the following rules:

- If the error undergoes four consecutive reductions, increase the step size by multiplying it by a constant (`StepSizeIncreaseRate`) greater than one.
- If the error undergoes two consecutive combinations of one increase and one reduction, decrease the step size by multiplying it by a constant (`StepSizeDecreaseRate`) less than one.

Ideally, the step size increases at the start of training, reaches a maximum, and then decreases for the remainder of the training. To achieve this step size profile, adjust the initial step size (`InitialStepSize`), step-size increase rate, and step-size decrease rate.

Display Options

When training using the `anfis` function, you can specify what training progress information to display in the MATLAB Command Window. Using an `anfisOptions` option set, you can set the following display options.

- `DisplayANFISInformation` — Display ANFIS information at the start of training
- `DisplayErrorValues` — Display the training error at each epoch
- `DisplayStepSize` — Display the step-size each time it changes.
- `DisplayFinalResults` — Display the final training error and validation error

Neuro-Fuzzy Designer does not provide user-specified display options. Instead, it displays the training progress as a plot.

Training Validation

Validation data lets you check the generalization capability of your trained fuzzy inference system. The validation data should fully represent the features of the data the FIS is intended to model, while also being sufficiently different from the training data to test training generalization. The software uses this data set to cross-validate the fuzzy inference model by applying the validation data to the model and seeing how well the model responds to this data.

Model validation is useful in the following situations:

- Noisy data — In some cases, data is collected using noisy measurements, and the training data is unable to represent all the features of the data the FIS is intended to model.
- Overfitting — Since the model structure used for ANFIS is fixed with a large number of parameters, there is a tendency for the model to overfit the data on which it is trained, especially when using a large number of training epochs. If overfitting does occur, the trained FIS may not generalize well to other independent data sets.

The idea behind using a checking data set for model validation is that, after a certain point in the training process, the model begins overfitting the training data set. In principle, the model error for the checking data set decreases up to the point that overfitting begins. After this point, the model error for the checking data increases. Overfitting is accounted for by testing the trained FIS against the checking data, and choosing the membership function parameters to be those associated with the minimum checking error if these errors indicate model overfitting.

Usually, the training and checking data sets are collected based on observations of the target system and are then stored in separate files. To specify validation data when using the:

- `anfis` function, create an `anfisOptions` object, and set the `ValidationData` option.
- **Neuro-Fuzzy Designer**, in the **Load data** section, select **Checking**.

The array and file formats for the checking data are the same as those for the training data.

Training Results

When you train your fuzzy system using the `anfis` function, you can obtain the following trained fuzzy systems:

- The `fis` output argument is the fuzzy system for which the training error is minimum. This system is always returned by the `anfis` function, and corresponds to the FIS returned by **Neuro-Fuzzy Designer** when you do not specify checking data.
- The `chkFIS` output argument is the fuzzy system for which the validation error is minimum. This system is returned only when you specify validation data using `anfisOptions`, and corresponds to the FIS returned by **Neuro-Fuzzy Designer** when you specify checking data. This FIS object is the one that you should use for further calculation if checking data is used for cross-validation.

You can obtain the error associated with each of the trained fuzzy systems. In each case, the returned error is the root mean squared error (RMSE), and is returned as a vector. Each element of the vector is the RMSE error value at each training epoch.

- Training error — Difference between the training data output value and the output of the fuzzy inference system for the corresponding training data input values.
- Validation error — Difference between the checking data output value and the output of the fuzzy inference system for the corresponding checking data input values. This error is returned only when you specify validation data using `anfisOptions`.

During training, the **Neuro-Fuzzy Designer** app plots the training and checking error for each training epoch. Exporting training and checking error from the app is not supported. To obtain the training error, you must retrain the system from the command-line. For an example, see “Save Training Error Data to MATLAB Workspace” on page 3-187.

To further test your trained fuzzy system, you can use an additional set of testing data that you did not use for training or validation. To do so:

- When training a system at the command-line, use the `evalfis` function.
- When using **Neuro-Fuzzy Designer**, in the **Load data** section, select **Testing**, and click **Load Data**. To evaluate the trained system for any loaded data set, in the **Test FIS** section, select a data set, and click **Test Now**.

Training Algorithm Differences

The **Neuro-Fuzzy Designer** app manages training epochs in a manner different from the `anfis` function. This difference produces variations in the training results.

To train a system for N epochs at the command line, you call the `anfis` function one time, specifying the number of epochs as N . However, the **Neuro-Fuzzy Designer** app calls the `anfis` function N times, specifying the number of epochs as 2 each time.

For a command-line example that demonstrates the **Neuro-Fuzzy Designer** training algorithm, see “Save Training Error Data to MATLAB Workspace” on page 3-187.

References

- [1] Jang, J.-S. R., "Fuzzy Modeling Using Generalized Neural Networks and Kalman Filter Algorithm," *Proc. of the Ninth National Conf. on Artificial Intelligence (AAAI-91)*, pp. 762-767, July 1991.
- [2] Jang, J.-S. R., "ANFIS: Adaptive-Network-based Fuzzy Inference Systems," *IEEE Transactions on Systems, Man, and Cybernetics*, Vol. 23, No. 3, pp. 665-685, May 1993.
- [3] Jang, J.-S.R., and N. Gulley. 'Gain Scheduling Based Fuzzy Controller Design'. In *NAFIPS/IFIS/ NASA '94. Proceedings of the First International Joint Conference of The North American Fuzzy Information Processing Society Biannual Conference. The Industrial Fuzzy Control and Intelligent Systems Conference, and the NASA Joint Technology Wo*, 101-5. San Antonio, TX, USA: IEEE, 1994.
- [4] Jang, J.-S.R. and Chuen-Tsai Sun. 'Neuro-Fuzzy Modeling and Control'. *Proceedings of the IEEE* 83, no. 3 (March 1995): 378-406.
- [5] Jang, Jyh-Shing Roger, Chuen-Tsai Sun, and Eiji Mizutani. *Neuro-Fuzzy and Soft Computing: A Computational Approach to Learning and Machine Intelligence*. MATLAB Curriculum Series. Upper Saddle River, NJ: Prentice Hall, 1997.
- [6] Wang, Li-Xin. *Adaptive Fuzzy Systems and Control: Design and Stability Analysis*. Englewood Cliffs, NJ: PTR Prentice Hall, 1994.
- [7] Widrow, B. and D. Stearns, *Adaptive Signal Processing*, Prentice Hall, 1985.

See Also

Apps

Neuro-Fuzzy Designer

Functions

`anfis`

More About

- “Train Adaptive Neuro-Fuzzy Inference Systems” on page 3-177
- “Save Training Error Data to MATLAB Workspace” on page 3-187
- “Predict Chaotic Time-Series Using ANFIS” on page 3-193

Train Adaptive Neuro-Fuzzy Inference Systems

This example shows how to create, train, and test Sugeno-type fuzzy systems using the **Neuro-Fuzzy Designer** app. For more information on:

- Neuro-adaptive fuzzy systems, see “Neuro-Adaptive Learning and ANFIS” on page 3-171.
- Training neuro-adaptive fuzzy systems at the command line, see `anfis`.


Load Training Data

Training and validating systems using the **Neuro-Fuzzy Designer** app requires data. Import the training data (`fuzex1trnData`) and validation data (`fuzex1chkData`) to the MATLAB workspace.

```
load fuzex1trnData.dat
load fuzex1chkData.dat
```


Open the **Neuro-Fuzzy Designer** app.

```
neuroFuzzyDesigner
```




Load the training data set from the workspace. In the **Load data** section, select **Training** and **worksp.**

Click **Load Data**. In the Load from workspace dialog box, enter the variable name `fuzex1trnData`.




Click **OK**. **Neuro-Fuzzy Designer** displays the training data in the plot as a set of circles.



Load the checking data from the MATLAB workspace into **Neuro-Fuzzy Designer**. In the **Load data** section, select **Checking**.

Load the checking data in the same manner as the training data, specifying the variable name `fuzex1chkData`. **Neuro-Fuzzy Designer** displays the checking data using plus signs superimposed on the training data.



To clear a specific data set from the app, in the **Load data** area, select the data **Type**, and click **Clear Data**.

Generate or Load FIS Structure

Before you start the FIS training, you must specify an initial FIS model structure. To specify the model structure, you perform one of the following tasks:


- Load a previously saved single-output Sugeno-type FIS object from a file or the MATLAB workspace.
- Generate the initial FIS model using grid partitioning.
- Generate the initial FIS model using subtractive clustering.

For this example, generate the initial FIS using grid partitioning. In **Neuro-Fuzzy Designer**, in the **Generate FIS** section, select **Grid partition**.

Click **Generate FIS**.

In the Add Membership Functions dialog box:

- In the **Input** section, in **Number of MFs**, specify the number of input membership functions. For this example, use 4 membership functions for all input variables.
- In **MF Type**, select `gbellmf` as the input membership function type.
- In the **Output** section, in **MF Type**, select `linear` as the output membership function type.



Interactively Specify FIS Structure

Alternatively, you can interactively specify your own FIS structure with specified membership functions and rules. The system you define must be a Sugeno system with the following properties:

- Single output
- Weighted average defuzzification
- First or zeroth order system; that is, all output membership functions must be the same type, either `'linear'` or `'constant'`.
- No rule sharing. Different rules cannot use the same output membership function; that is, the number of output membership functions must equal the number of rules.
- Unity weight for each rule.
- No custom membership functions or defuzzification methods.


To define the:

- Membership functions for each variable, in **Neuro-Fuzzy Designer**, select **Edit > Membership Functions**. Then, in the Membership Function Editor window, define the membership functions.
- Rules, in **Neuro-Fuzzy Designer**, select **Edit > Rules**. Then, in the Rule Editor window, define the rules.

These tools are the same as those used by the **Fuzzy Logic Designer** app. For more information, see “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14.

View FIS Structure

After you load or generate the FIS, you can view the model structure. To do so, in **Neuro-Fuzzy Designer**, click **Structure**.



The branches in this graph are color coded. Color coding of branches characterize the rules and indicate whether or not AND, NOT, or OR are used in the rules. The input is represented by the left-most node and the output by the right-most node. The node represents a normalization factor for the rules. To view information about the structure, click on each node.

Also, to view the FIS:


- Membership functions, in **Neuro-Fuzzy Designer**, select **Edit > Membership Functions**.
- Rules, in **Neuro-Fuzzy Designer**, select **Edit > Rules**.

Train FIS

After loading the training data and generating the initial FIS structure, you can train your FIS. To do so, in **Neuro-Fuzzy Designer**, in the **Train FIS** section, specify the following parameters.

- **Optim. Method** — Optimization method. For this example, select the **hybrid** method, which uses a combination of backpropagation and least-squares regression to tune the FIS parameters.
- **Epochs** — Number of training epochs. For this example, specify **40** epochs.
- **Error Tolerance** — Error tolerance stopping condition. For this example, specify a value of **0**, which indicates that the training will stop when the number of training epochs is reached.

To train the FIS, click **Train Now**.



The app trains the FIS and plots the training error (as stars) and checking error (as dots) for each training epoch.

The checking error decreases up to a certain point in the training, and then it increases. This increase occurs at the point where the training starts overfitting the training data. The app selects the FIS associated with this overfitting point as the trained ANFIS model.

Validate Trained FIS

After the FIS is trained, validate the model using a **Testing** or **Checking** data set that differs from the training data. For this example, use the previously loaded checking data.

To test your FIS against the checking data, in the **Test FIS** section, select **Checking data**. Then, click **Test Now**.



The app plots the output values of the testing data set (using blue +'s) and the output of the trained FIS for the corresponding testing data input values (using red *'s). The FIS output values correlate well with the expected output.

Importance of Checking Data

It is important to have checking data that fully represents the features of the data the FIS is intended to model. If your checking data is significantly different from your training data and does not cover the same data features to model as the training data, then the training results will be poor.


For example, load new training and checking data into **Neuro-Fuzzy Designer**. This data has significantly different training and checking sets.

- 1 At the MATLAB command line, load the training and checking data.


```
load fuzex2trnData.dat
load fuzex2chkData.dat
```

- 2 Clear the previously loaded training and checking data. In the **Load data** section, select each data type, click **Clear Data**.

- 3 Load the training data (fuzex2trnData) and checking data (fuzex2chkData), as you did previously.




Generate a FIS structure and train the FIS as you did previously, except now select 60 training epochs.



In this case, the checking error is large, with the minimum occurring in the first epoch. Since the app chooses the trained FIS parameters associated with the minimum checking error, the trained FIS does not sufficiently capture the features of this data set. It is important to know the features of your data set well when you select your training and checking data. When you do not know the features of your data, you can analyze the checking error plots to see whether or not the checking data performed sufficiently well with the trained model.

In this example, the checking error is sufficiently large to indicate that either you need to select more data for training or modify your membership function choices (both the number of membership functions and the type). Otherwise, if you think the training data sufficiently captures the features you are trying to represent, the system can be retrained without the checking data.

To verify the poor training results, test the trained FIS model against the checking data.



As expected, there are significant differences between the checking data output values and the FIS output.

See Also

Neuro-Fuzzy Designer

More About

- “Neuro-Adaptive Learning and ANFIS” on page 3-171
- “Save Training Error Data to MATLAB Workspace” on page 3-187

Save Training Error Data to MATLAB Workspace

When using **Neuro-Fuzzy Designer**, you can export your initial FIS structure to the MATLAB workspace and then generate ANFIS training error values. Since exporting the training and validation error profiles from the **Neuro-Fuzzy Designer** app is not supported, use this method to generate such error plots.


The following example shows how to save the training error generated during ANFIS training to the MATLAB workspace.

- 1 Load your training data (`fuzex1trnData`) and validation data (`fuzex1chkData`) to the MATLAB workspace.

```
load fuzex1trnData.dat
load fuzex1chkData.dat
```


- 2 Open the **Neuro-Fuzzy Designer** app.

```
neuroFuzzyDesigner
```




- 3 Load the training data from the MATLAB workspace into **Neuro-Fuzzy Designer**.
 - a In the **Load data** section, select **Training**.

- b Select **worksp.**
- c Click **Load Data**. In the Load from workspace dialog box, enter the variable name `fuzex1trnData`.




- d Click **OK**. **Neuro-Fuzzy Designer** displays the training data in the plot as a set of circles.




- 4 Load the checking data from the MATLAB workspace into **Neuro-Fuzzy Designer**. In the **Load data** section, select **Checking**.


Load the checking data in the same manner as the training data, specifying the variable name `fuzex1chkData`. **Neuro-Fuzzy Designer** displays the checking data using plus signs superimposed on the training data.



- 5 Generate an initial FIS.
 - a In the **Generate FIS** section, select **Grid partition**.
 - b Click **Generate FIS**.
 - c In the Add Membership Functions dialog box:
 - In the **Input** section, in **Number of MFs**, specify the number of input membership functions. For this example use 4 for all input variables.
 - In **MF Type**, select `gbellmf` as the input membership function type.
 - In the **Output** section, in **MF Type**, select `linear` as the output membership function type.



- d Click **OK**.
- 6 Export the initial FIS to the MATLAB workspace.
- a In **Neuro-Fuzzy Designer**, select **File > Export > To Workspace**.
- This action opens a dialog box where you specify the MATLAB variable name.
- b In the Export To Workspace dialog box, in the **Workspace variable** field, enter `initfis` as the variable name.



- c Click **OK**. The app exports the FIS object to the MATLAB workspace.
- 7 Train the FIS for 40 epochs. Instead of using a single call to the `anfis` function, call the function inside a loop using 2 epochs for each call. This training method replicates the training process used by the **Neuro-Fuzzy Designer** app.

At each training epoch, save the training and validation errors.


```

fis = initfis;
opt = anfisOptions('EpochNumber',2,'ValidationData',fuzexlchkData);
trainError = zeros(1,40);
checkError = zeros(1,40);
for ct = 1:40
    opt.InitialFIS = fis;
    [fis,error,~,~,chkError] = anfis(fuzexltrnData,opt);
    trainError(ct) = error(1);
    checkError(ct) = chkError(1);
end


```

- 8 Plot the training and validation errors over the training process. These error values are the root mean squared errors at each training epoch.

```

epochNum = 1:40;
plot(epochNum,trainError,'b*',epochNum,checkError,'ro')
xlabel('Epoch Number')
ylabel('Error')
legend('Training Error','Validation Error')

```



These error profiles are similar to the error profiles when the same initial FIS structure is trained in the **Neuro-Fuzzy Designer** app.

See Also
Neuro-Fuzzy Designer

More About

- “Neuro-Adaptive Learning and ANFIS” on page 3-171
- “Train Adaptive Neuro-Fuzzy Inference Systems” on page 3-177

Predict Chaotic Time-Series Using ANFIS

This example shows how to do chaotic time-series prediction using ANFIS.

Time Series Data

This example uses `anfis` to predict a time series generated by the following Mackey-Glass (MG) time-delay differential equation.


$$\dot{x}(t) = \frac{0.2x(t-\tau)}{1+x^{10}(t-\tau)} - 0.1x(t)$$

This time series is chaotic with no clearly defined period. The series does not converge or diverge, and the trajectory is highly sensitive to initial conditions. This benchmark problem is used in the neural network and fuzzy modeling research communities.

To obtain the time series value at integer points, the fourth-order Runge-Kutta method was used to find the numerical solution to the previous MG equation. It was assumed that $x(0) = 1.2$, $\tau = 17$, and $x(t) = 0$ for $t < 0$. The result was saved in the file `mgdata.dat`.

Load and plot the MG time series.

```
load mgdata.dat
time = mgdata(:,1);
x = mgdata(:, 2);
figure(1)
plot(time,x)
title('Mackey-Glass Chaotic Time Series')
xlabel('Time (sec)')
ylabel('x(t)')
```



Preprocess Data

In time-series prediction, you use known values of the time series up to point in time, t , to predict the value at some point in the future, $t + P$. The standard method for this type of prediction is to create a mapping from D sample data points, sampled every Δ units in time ($x(t - (D - 1)\Delta), \dots, x(t - \Delta), x(t)$) to a predicted future value $x = (t + P)$. Following the conventional settings for predicting the MG time series, set $D = 4$ and $\Delta = P = 6$. For each t , the input training data for `anfis` is a four-column vector of the following form.

$$w(t) = [x(t - 19), x(t - 12), x(t - 6), x(t)]$$

The output training data corresponds to the trajectory prediction.

$$s(t) = x(t + 6)$$

For each t , ranging in values from 118 to 1117, there are 1000 input/output training samples. For this example, use the first 500 samples as training data (`trnData`) and the second 500 values as checking data for validation (`chkData`). Each row of the training and checking data arrays contains one sample point where the first four columns contain the four-dimensional input w and the fifth column contains the output s .

Construct the training and checking data arrays.

```
for t = 118:1117
    Data(t-117,:) = [x(t-18) x(t-12) x(t-6) x(t) x(t+6)];
end
```

```
trnData = Data(1:500,:);
chkData = Data(501:end,:);
```

Build Initial Fuzzy System


Create an initial Sugeno FIS object for training using the `genfis` function with grid partitioning.

```
fis = genfis(trnData(:,1:end-1),trnData(:,end),...
    genfisOptions('GridPartition'));
```

The number of FIS inputs and outputs corresponds to the number of columns in the input and output training data, four and one, respectively.

By default, `genfis` creates two generalized bell membership functions for each of the four inputs. The initial membership functions for each variable are equally spaced and cover the whole input space.

```
figure
subplot(2,2,1)
plotmf(fis,'input',1)
subplot(2,2,2)
plotmf(fis,'input',2)
subplot(2,2,3)
plotmf(fis,'input',3)
subplot(2,2,4)
plotmf(fis,'input',4)
```



The generated FIS object contains $2^4 = 16$ fuzzy rules with 104 parameters (24 nonlinear parameters and 80 linear parameters). To achieve good generalization capability, it is important that the number of training data points be several times larger than the number parameters being estimated. In this case, the ratio between data and parameters is approximately five (500/104), which is a good balance between fitting parameters and training sample points.

Train ANFIS Model

To configure training options, create an `anfisOptions` option set, specifying the initial FIS and validation data.

```
options = anfisOptions('InitialFIS',fis,'ValidationData',chkData);
```

Train the FIS using the specified training data and options.

```
[fis1,error1,ss,fis2,error2] = anfis(trnData,options);
```

ANFIS info:

```
Number of nodes: 55
Number of linear parameters: 80
Number of nonlinear parameters: 24
Total number of parameters: 104
Number of training data pairs: 500
Number of checking data pairs: 500
Number of fuzzy rules: 16
```

Start training ANFIS ...

```
1      0.00296046      0.00292488
2      0.00290346      0.0028684
3      0.00285048      0.00281544
4      0.00280117      0.00276566
Step size increases to 0.011000 after epoch 5.
5      0.00275517      0.00271874
6      0.00271214      0.00267438
7      0.00266783      0.00262818
8      0.00262626      0.00258435
Step size increases to 0.012100 after epoch 9.
9      0.00258702      0.00254254
10     0.00254972      0.00250247
```

Designated epoch number reached. ANFIS training completed at epoch 10.

```
Minimal training RMSE = 0.00254972
Minimal checking RMSE = 0.00250247
```

`fis1` is the trained fuzzy inference system for the training epoch where the training error is smallest. Since you specified validation data, the fuzzy system with the minimum checking error, `fis2`, is also returned. The FIS with the smallest checking error shows the best generalization beyond the training data.


Plots the membership functions for the trained system.

```
figure
subplot(2,2,1)
plotmf(fis2,'input',1)
```

```

subplot(2,2,2)
plotmf(fis2,'input',2)
subplot(2,2,3)
plotmf(fis2,'input',3)
subplot(2,2,4)
plotmf(fis2,'input',4)

```




Plot Errors Curves

Plot the training and checking error signals.

```

figure
plot([error1 error2])
hold on
plot([error1 error2],'o')
legend('Training error','Checking error')
xlabel('Epochs')
ylabel('Root Mean Squared Error')
title('Error Curves')

```




The training error is higher than the checking error in all epochs. This phenomenon is not uncommon in ANFIS learning or nonlinear regression in general; it could indicate that additional training could produce better training results.

Compare Original and Predicted Series

To check prediction capability of the trained system, evaluate the fuzzy system using the training and checking data, and plot the result alongside the original

```
anfis_output = evalfis(fis2,[trnData(:,1:4); chkData(:,1:4)]);
```


```
figure
index = 125:1124;
plot(time(index),[x(index) anfis_output])
xlabel('Time (sec)')
title('MG Time Series and ANFIS Prediction')
```

The predicted series is similar to the original series.

Calculate and plot the prediction error.

```
diff = x(index) - anfis_output;  
plot(time(index),diff)  
xlabel('Time (sec)')  
title('Prediction Errors')
```



The scale of the prediction error plot is about one-hundredth of the scale of the time-series plot. In this example, you trained the system for only 10 epoch. Training for additional epochs can improve the training results.

See Also

`anfis` | `genfis` | `evalfis`

More About

- “Neuro-Adaptive Learning and ANFIS” on page 3-171

Modeling Inverse Kinematics in a Robotic Arm

This example shows how to use a fuzzy system to model the inverse kinematics in a two-joint robotic arm.

What Is Inverse Kinematics?

Kinematics is the science of motion. In a two-joint robotic arm, given the angles of the joints, the kinematics equations give the location of the tip of the arm. Inverse kinematics refers to the reverse process. Given a desired location for the tip of the robotic arm, what should the angles of the joints be so as to locate the tip of the arm at the desired location. There is usually more than one solution and can at times be a difficult problem to solve.

This is a typical problem in robotics that needs to be solved to control a robotic arm to perform tasks it is designated to do. In a 2-dimensional input space, with a two-joint robotic arm and given the desired coordinate, the problem reduces to finding the two angles involved. The first angle is between the first arm and the ground (or whatever it is attached to). The second angle is between the first arm and the second arm.




Figure 1: Illustration showing the two-joint robotic arm with the two angles, θ_1 and θ_2

Why Use Fuzzy Logic?

For simple structures like the two-joint robotic arm, it is possible to mathematically deduce the angles at the joints given the desired location of the tip of the arm. However with more complex structures (for example: n -joint robotic arms operating in a 3-dimensional input space) deducing a mathematical solution for the inverse kinematics may prove challenging.

Using fuzzy logic, we can construct a fuzzy inference system that deduces the inverse kinematics if the forward kinematics of the problem is known, hence sidestepping the need to develop an analytical solution. Also, the fuzzy solution is easily understandable and does not require special background knowledge to comprehend and evaluate it.

In the following section, a broad outline for developing such a solution is described, and later, the detailed steps are elaborated.

Overview of Fuzzy Solution

Since the forward kinematics formulae for the two-joint robotic arm are known, x and y coordinates of the tip of the arm are deduced for the entire range of angles of rotation of the two joints. The coordinates and the angles are saved to be used as training data to train an ANFIS (adaptive neuro-fuzzy inference system) network.

During training, the ANFIS network learns to map the coordinates (x, y) to the angles (θ_1 , θ_2). The trained ANFIS network is then used as a part of a larger control system to control the robotic arm. Knowing the desired location of the robotic arm, the control system uses the trained ANFIS network to deduce the angular positions of the joints and applies force to the joints of the robotic arm accordingly to move it to the desired location.

What Is ANFIS?

ANFIS stands for adaptive neuro-fuzzy inference system. It is a hybrid neuro-fuzzy technique that brings learning capabilities of neural networks to fuzzy inference systems. The learning algorithm tunes the membership functions of a Sugeno-type fuzzy inference system using the training input/output data.

In this case, the input/output data refers to the "coordinates/angles" dataset. The coordinates act as input to the ANFIS and the angles act as the output. The learning algorithm teaches the ANFIS to map the coordinates to the angles through a process called training. At the end of training, the trained ANFIS network would have learned the input-output map and be ready to be deployed into the larger control system solution.

Data Generation

Let θ_1 be the angle between the first arm and the ground. Let θ_2 be the angle between the second arm and the first arm (Refer to Figure 1 for illustration). Let the length of the first arm be l_1 and that of the second arm be l_2 .

Assume that the first joint has limited freedom to rotate and it can rotate between 0 and 90 degrees. Similarly, assume that the second joint has limited freedom to rotate and can rotate between 0 and 180 degrees. (This assumption takes away the need to handle some special cases which will confuse the discourse.) Hence, $0 \leq \theta_1 \leq \pi/2$ and $0 \leq \theta_2 \leq \pi$.




Figure 2: Illustration showing all possible theta1 and theta2 values.

Now, for every combination of theta1 and theta2 values the x and y coordinates are deduced using forward kinematics formulae.

The following code snippet shows how data is generated for all combination of theta1 and theta2 values and saved into a matrix to be used as training data. The reason for saving the data in two matrices is explained in the following section.

```

l1 = 10; % length of first arm
l2 = 7; % length of second arm

theta1 = 0:0.1:pi/2; % all possible theta1 values
theta2 = 0:0.1:pi; % all possible theta2 values

[THETA1,THETA2] = meshgrid(theta1,theta2); % generate grid of angle values

X = l1 * cos(THETA1) + l2 * cos(THETA1 + THETA2); % compute x coordinates
Y = l1 * sin(THETA1) + l2 * sin(THETA1 + THETA2); % compute y coordinates

data1 = [X(:) Y(:) THETA1(:)]; % create x-y-theta1 dataset
data2 = [X(:) Y(:) THETA2(:)]; % create x-y-theta2 dataset

```

The following plot shows all the X-Y data points generated by cycling through different combinations of θ_1 and θ_2 and deducing x and y coordinates for each. The plot can be generated by using the following code. The plot is annotated further for easier understanding.

```
plot(X(:),Y(:),'r. ');
axis equal;
xlabel('X','fontsize',10)
ylabel('Y','fontsize',10)
title('X-Y coordinates for all theta1 and theta2 combinations','fontsize',10)
```




Figure 3: X-Y coordinates generated for all θ_1 and θ_2 combinations using forward kinematics formulae

Building ANFIS Networks

One approach to building an ANFIS solution for this problem, is to build two ANFIS networks, one to predict θ_1 and the other to predict θ_2 .

In order for the ANFIS networks to be able to predict the angles they have to be trained with sample input-output data. The first ANFIS network will be trained with X and Y coordinates as input and corresponding θ_1 values as output. The matrix `data1` contains the x-y- θ_1 dataset required to train the first ANFIS network. Therefore `data1` will be used as the dataset to train the first ANFIS network.

Similarly, the second ANFIS network will be trained with X and Y coordinates as input and corresponding `theta2` values as output. The matrix `data2` contains the `x-y-theta2` dataset required to train the second ANFIS network. Therefore `data2` will be used as the dataset to train the second ANFIS network.

To train an ANFIS network, first specify the training options using the `anfisOptions` command. For this example, specify an FIS object with 7 membership functions for each input variable. Train the system for 150 epochs and suppress the Command Window display of training information.

```
opt = anfisOptions;
opt.InitialFIS = 7;
opt.EpochNumber = 150;
opt.DisplayANFISInformation = 0;
opt.DisplayErrorValues = 0;
opt.DisplayStepSize = 0;
opt.DisplayFinalResults = 0;
```

Train an ANFIS system using the first set of training data, `data1`.

```
disp('--> Training first ANFIS network.')
```

```
--> Training first ANFIS network.
```

```
anfis1 = anfis(data1,opt);
```

Change the number of input membership functions and train an ANFIS system using the second set of training data, `data2`.

```
disp('--> Training second ANFIS network.')
```

```
--> Training second ANFIS network.
```

```
opt.InitialFIS = 6;
anfis2 = anfis(data2,opt);
```

For this example, the number of input membership functions and training epochs were selected based on experimentation with different potential values.

`anfis1` and `anfis2` represent the two trained ANFIS networks that will be deployed in the larger control system.

Once the training is complete, the two ANFIS networks have learned to approximate the angles (`theta1`, `theta2`) as a function of the coordinates (`x`, `y`). One advantage of using the fuzzy approach is that the ANFIS network can now approximate the angles for coordinates that are similar but not exactly the same as it was trained with. For example, the trained ANFIS networks are now capable of approximating the angles for coordinates that lie between two points that were included in the training dataset. This will allow the final controller to move the arm smoothly in the input space.

We now have two trained ANFIS networks which are ready to be deployed into the larger system that will utilize these networks to control the robotic arms.

Validating ANFIS Networks

Having trained the networks, an important follow up step is to validate the networks to determine how well the ANFIS networks would perform inside the larger control system.

Since this example problem deals with a two-joint robotic arm whose inverse kinematics formulae can be derived, it is possible to test the answers that the ANFIS networks produce with the answers from the derived formulae.

Assume that it is important for the ANFIS networks to have low errors within the operating range $0 < x < 2$ and $8 < y < 10$.

```
x = 0:0.1:2; % x coordinates for validation
y = 8:0.1:10; % y coordinates for validation
```

The `theta1` and `theta2` values are deduced mathematically from the `x` and `y` coordinates using inverse kinematics formulae.

```
[X,Y] = meshgrid(x,y);
c2 = (X.^2 + Y.^2 - l1^2 - l2^2)/(2*l1*l2);
s2 = sqrt(1 - c2.^2);
THETA2D = atan2(s2,c2); % theta2 is deduced
k1 = l1 + l2.*c2;
k2 = l2*s2;
THETA1D = atan2(Y,X) - atan2(k2,k1); % theta1 is deduced
```

`THETA1D` and `THETA2D` are the variables that hold the values of `theta1` and `theta2` deduced using the inverse kinematics formulae.

`theta1` and `theta2` values predicted by the trained ANFIS networks are obtained by using the command `evalfis` which evaluates a FIS for the given inputs.

Here, `evalfis` is used to find out the FIS outputs for the same `x-y` values used earlier in the inverse kinematics formulae.


```
XY = [X(:) Y(:)];
THETA1P = evalfis(anfis1,XY); % theta1 predicted by anfis1
THETA2P = evalfis(anfis2,XY); % theta2 predicted by anfis2
```

Now, we can see how close the FIS outputs are with respect to the deduced values.

```
thetaldiff = THETA1D(:) - THETA1P;
theta2diff = THETA2D(:) - THETA2P;

subplot(2,1,1)
plot(thetaldiff)
ylabel('THETA1D - THETA1P')
title('Deduced theta1 - Predicted theta1')

subplot(2,1,2)
plot(theta2diff)
ylabel('THETA2D - THETA2P')
title('Deduced theta2 - Predicted theta2')
```

The errors are in the $1e-3$ range which is a fairly good number for the application it is being used in. However this may not be acceptable for another application, in which case the parameters to the `anfis` function may be tweaked until an acceptable solution is arrived at. Also, other techniques like input selection and alternate ways to model the problem may be explored.

Building a Solution Around the Trained ANFIS Networks

Now given a specific task, such as robots picking up an object in an assembly line, the larger control system will use the trained ANFIS networks as a reference, much like a lookup table, to determine what the angles of the arms must be, given a desired location for the tip of the arm. Knowing the desired angles and the current angles of the joints, the system will apply force appropriately on the joints of the arms to move them towards the desired location.

The `invkine` command launches a GUI that shows how the two trained ANFIS networks perform when asked to trace an ellipse.




Figure 4: GUI for Inverse Kinematics Modeling.

The two ANFIS networks used in the example have been pretrained and are deployed into a larger system that controls the tip of the two-joint robot arm to trace an ellipse in the input space.

The ellipse to be traced can be moved around. Move the ellipse to a slightly different location and observe how the system responds by moving the tip of the robotic arm from its current location to the closest point on the new location of the ellipse. Also observe that the system responds smoothly as long as the ellipse to be traced lies within the 'x' marked spots which represent the data grid that was used to train the networks. Once the ellipse is moved outside the range of data it was trained with, the ANFIS networks respond unpredictably. This emphasizes the importance of having relevant and representative data for training. Data must be generated based on the expected range of operation to avoid such unpredictability and instability issues.

See Also

`anfis` | `evalfis`

More About

- “Neuro-Adaptive Learning and ANFIS” on page 3-171


Adaptive Noise Cancellation Using ANFIS

This example shows how to do adaptive nonlinear noise cancellation by constructing and tuning an ANFIS model.

Signal and Noise

Define a hypothetical information signal, x , sampled at 100 Hz over 6 seconds.


```
time = (0:0.01:6)';
x = sin(40./(time+0.01));
plot(time,x)
title('Information Signal x')
xlabel('time')
ylabel('x')
```



Assume that x cannot be measured without an interference signal, n_2 , which is generated from another noise source, n_1 , by a certain unknown nonlinear process.

Generate and plot the noise source n_1 .

```
n1 = randn(size(time));
plot(time,n1)
title('Noise Source n_1')
xlabel('time')
ylabel('n_1')
```




Assume that the interference signal, n_2 , that appears in the measured signal is generated via an unknown nonlinear equation:

$$n_2(k) = \frac{4\sin(n_1(k)) \cdot n_1(k-1)}{1 + n_1(k-1)^2}$$

Plot this nonlinear function as a surface.

```
domain = linspace(min(n1),max(n1),20);
[xx,yy] = meshgrid(domain,domain);
zz = 4*sin(xx).*yy./(1+yy.^2);


surf(xx,yy,zz)
xlabel('n_1(k)')
ylabel('n_1(k-1)')
zlabel('n_2(k)')
title('Unknown Interference Channel Characteristics')
```



Compute the interference signal, n_2 , from the noise source, n_1 , and plot both signals.

```
n1d0 = n1; % n1 with delay 0
n1d1 = [0; n1d0(1:length(n1d0)-1)]; % n1 with delay 1
n2 = 4*sin(n1d0).*n1d1./(1+n1d1.^2); % interference


subplot(2,1,1)
plot(time,n1)
ylabel('n_1')
xlabel('time')
title('Noise Source')
subplot(2,1,2)
plot(time,n2)
ylabel('n_2')
title('Interference Signal')
xlabel('time')
```



n_2 is related to n_1 by the highly nonlinear process shown previously. However, from the plots, these two signals do not appear to correlate with each other in any way.

The measured signal, m , is the sum of the original information signal, x , and the interference, n_2 . However, n_2 is unknown. The only available signals are the noise signal, n_1 , and the measured signal m .

```
m = x + n2;  
subplot(1,1,1)  
plot(time, m)  
title('Measured Signal')  
xlabel('time')  
ylabel('m')
```



You can recover the original information signal, x , using adaptive noise cancellation via ANFIS training.

Build the ANFIS Model

Use the `anfisc` command to identify the nonlinear relationship between n_1 and n_2 . While n_2 is not directly available, you can assume that m is a noisy version of n_2 for training. This assumption treats x as "noise" in this kind of nonlinear fitting.

Assume the order of the nonlinear channel is known (in this case, 2). You can use a two-input ANFIS model for training.

Define the training data. The first two columns of `data` are the inputs to the ANFIS model, n_1 and a delayed version of n_1 . The final column of `data` is the measured signal, m .

```
delayed_n1 = [0; n1(1:length(n1)-1)];
data = [delayed_n1 n1 m];
```

Generate the initial FIS object. By default, the grid partitioning algorithm uses two membership functions for each input variable, which produces four fuzzy rules for learning.

```
genOpt = genfisOptions('GridPartition');
inFIS = genfis(data(:,1:end-1),data(:,end),genOpt);
```

Tune the FIS using the `anfisc` command with an initial training step size of 0.2.

```
trainOpt = anfisOptions('InitialFIS',inFIS,'InitialStepSize',0.2);  
outFIS = anfis(data,trainOpt);
```

ANFIS info:

```
Number of nodes: 21  
Number of linear parameters: 12  
Number of nonlinear parameters: 12  
Total number of parameters: 24  
Number of training data pairs: 601  
Number of checking data pairs: 0  
Number of fuzzy rules: 4
```

Start training ANFIS ...

```
1      0.761817  
2      0.748426  
3      0.739315  
4      0.733993  
Step size increases to 0.220000 after epoch 5.  
5      0.729492  
6      0.725382  
7      0.721269  
8      0.717621  
Step size increases to 0.242000 after epoch 9.  
9      0.714474  
10     0.71207
```

Designated epoch number reached. ANFIS training completed at epoch 10.

Minimal training RMSE = 0.71207

The tuned FIS, outFIS, models the second-order relationship between n_1 and n_2 .


Evaluate Model

Calculate the estimated interference signal, estimated_n2, by evaluating the tuned FIS using the original training data.

```
estimated_n2 = evalfis(outFIS,data(:,1:2));
```

Plot the actual n_2 signal and the estimated version from the ANFIS output.

```
subplot(2,1,1)  
plot(time, n2)  
ylabel('n_2')  
xlabel('time')  
title('Unknown Interference Signal')  
subplot(2,1,2)  
plot(time, estimated_n2)  
ylabel('n_2')  
xlabel('time')  
title('Estimated Interference Signal')
```





The estimated information signal is equal to the difference between the measured signal, m , and the estimated interference (ANFIS output).

```
estimated_x = m - estimated_n2;
```

Compare the original information signal, x , and the estimate, $estimated_x$.

```
figure
plot(time,estimated_x,'b',time,x,'r')
xlabel('time')
ylabel('x')
title('Comparison of Actual and Estimated Signals')
legend('Estimated x','Actual x (unknown)','Location','SouthEast')
```



Without extensive training, the ANFIS model produces a relatively accurate estimate of the information signal.

See Also

`anfis` | `genfis` | `evalfis`

More About


- "Neuro-Adaptive Learning and ANFIS" on page 3-171

Nonlinear System Identification

This example shows how to perform dynamic system identification by using a linear ARX and a nonlinear ANFIS model.

Load Data

The data set used in this example for ANFIS and ARX modeling is from a "Feedback's Process Trainer PT 326" laboratory device [1]. The device functions like a hair dryer: air is fanned through a tube and heated at the inlet. A thermocouple measures the air temperature. The input $u(k)$ is the voltage over a mesh of resistor wires to heat incoming air and the output $y(k)$ is the outlet air temperature.




Load the test data and plot the input and output.

```

load dryerdata
data_n = length(y);
output = y;
input = [[0; y(1:data_n-1)] ...
         [0; 0; y(1:data_n-2)] ...
         [0; 0; 0; y(1:data_n-3)] ...
         [0; 0; 0; 0; y(1:data_n-4)] ...
         [0; u(1:data_n-1)] ...
         [0; 0; u(1:data_n-2)] ...
         [0; 0; 0; u(1:data_n-3)] ...
         [0; 0; 0; 0; u(1:data_n-4)] ...
         [0; 0; 0; 0; 0; u(1:data_n-5)] ...
         [0; 0; 0; 0; 0; 0; u(1:data_n-6)]];
data = [input output];
data(1:6,:) = [];
input_name = ["y(k-1)", "y(k-2)", "y(k-3)", "y(k-4)", ...
              "u(k-1)", "u(k-2)", "u(k-3)", "u(k-4)", "u(k-5)", "u(k-6)"];
index = 1:100;

figure
subplot(2,1,1)
plot(index,y(index), "- ", index,y(index), "o")
title("Output Data")
ylabel("y(k)")
subplot(2,1,2)
plot(index,u(index), "- ", index,u(index), "o")
title("Input Data")
ylabel("u(k)")
  
```



The data points reflect a sample time of 0.08 seconds. The input $u(k)$ is a binary random signal shifting between 3.41 and 6.41. The probability of shifting the input at each sample is 0.2. The data set contains 1000 input/output data points. These plots show the output temperature $y(k)$ and input voltage $u(k)$ for the first 100 time steps.

Identify ARX Model

An ARX model is a linear model of the following form:

$$y(k) + a_1 \cdot y(k-1) + \dots + a_m \cdot y(k-m) = b_1 \cdot u(k-d) + \dots + b_n \cdot u(k-d-n+1)$$

Here:

- $y(k)$ and $u(k)$ are mean-subtracted versions of the original data.
- a_i and b_j are linear parameters.
- m , n , and d are three integers that exactly specify the ARX model.

To find an ARX model for the dryer device, first divide the data set into a training ($k = 1$ to 300) and a validation ($k = 301$ to 600) set.

```
trn_data_n = 300;
total_data_n = 600;
z = [y u];
z = dtrend(z);
ave = mean(y);
ze = z(1:trn_data_n,:);
```

```
zv = z(trn_data_n+1:total_data_n,:);
T = 0.08;
```

Perform an exhaustive search to find the best combination of m , n , and d , allowing each integer to change from 1 to 10 independently. To perform the search and select the ARX parameters, use the `arxstruc` (System Identification Toolbox) and `selstruc` (System Identification Toolbox) functions.

```
% Run through all different models.
V = arxstruc(ze,zv,struc(1:10,1:10,1:10));
% Find the best model.
nn = selstruc(V,0);
% Display model parameters
disp("[m n d] = " + num2str(nn))
```

```
[m n d] = 5 10 2
```

The best ARX model has $m = 5$, $n = 10$, and $d = 2$. Create with a training root mean squared error (RMSE) of 0.1122 and a validation RMSE of 0.0749. Plot the original $y(k)$ along with this ARX model.


Create and simulate an ARX model with these parameters.

```
th = arx(ze,nn);
th.Ts = 0.08;
u = z(:,2);
y = z(:,1) + ave;
yp = sim(u,th) + ave;
```

Plot the ARX model output against the training and validation data. The training root mean squared error (RMSE) is 0.1121 and the validation RMSE is 0.0748.

```
figure
subplot(2,1,1)
index = 1:trn_data_n;
plot(index,y(index),index,yp(index),'.')
rmse = norm(y(index)-yp(index))/sqrt(length(index));
title("Training Data (solid), ARX Prediction (dots)" ...
      + newline + "RMSE = " + num2str(rmse))
xlabel("Time Steps")

subplot(2,1,2)
index = (trn_data_n+1):(total_data_n);
plot(index,y(index),index,yp(index),'.')
rmse = norm(y(index)-yp(index))/sqrt(length(index));
title("Validation Data (solid), ARX Prediction (dots)" ...
      + newline + "RMSE = " + num2str(rmse))
xlabel("Time Steps")
```



Identify ANFIS Model

The ARX model is linear and can perform model structure and parameter identification rapidly. The performance in the previous plots appears to be satisfactory. However, if you want better performance, you can try a nonlinear model such as an adaptive neuro-fuzzy inference system (ANFIS).

To use an ANFIS for system identification, first determine which variables to use for the input arguments. For simplicity, use 10 input candidates ($y(k-1)$, $y(k-2)$, $y(k-3)$, $y(k-4)$, $u(k-1)$, $u(k-2)$, $u(k-3)$, $u(k-4)$, $u(k-5)$, and $u(k-6)$). Use $y(k)$ as the output.

Perform a sequential forward search of the inputs using the function `sequentialSearch`. This function selects each input variable sequentially to optimize the RMSE.

```
trn_data_n = 300;
trn_data = data(1:trn_data_n,:);
val_data = data(trn_data_n+1:trn_data_n+300,:);
[~,elapsed_time] = sequentialSearch(3,trn_data,val_data,input_name);
```

Selecting input 1 ...

```
Model 1: y(k-1), Error: trn = 0.2043, val = 0.1888
Model 2: y(k-2), Error: trn = 0.3819, val = 0.3541
Model 3: y(k-3), Error: trn = 0.5245, val = 0.4903
Model 4: y(k-4), Error: trn = 0.6308, val = 0.5977
Model 5: u(k-1), Error: trn = 0.8271, val = 0.8434
Model 6: u(k-2), Error: trn = 0.7976, val = 0.8087
Model 7: u(k-3), Error: trn = 0.7266, val = 0.7349
```


Model 8: $u(k-4)$, Error: trn = 0.6215, val = 0.6346
 Model 9: $u(k-5)$, Error: trn = 0.5419, val = 0.5650
 Model 10: $u(k-6)$, Error: trn = 0.5304, val = 0.5601
 Currently selected inputs: $y(k-1)$

Selecting input 2 ...

Model 11: $y(k-1) y(k-2)$, Error: trn = 0.1085, val = 0.1024
 Model 12: $y(k-1) y(k-3)$, Error: trn = 0.1339, val = 0.1283
 Model 13: $y(k-1) y(k-4)$, Error: trn = 0.1542, val = 0.1461
 Model 14: $y(k-1) u(k-1)$, Error: trn = 0.1892, val = 0.1734
 Model 15: $y(k-1) u(k-2)$, Error: trn = 0.1663, val = 0.1574
 Model 16: $y(k-1) u(k-3)$, Error: trn = 0.1082, val = 0.1077
 Model 17: $y(k-1) u(k-4)$, Error: trn = 0.0925, val = 0.0948
 Model 18: $y(k-1) u(k-5)$, Error: trn = 0.1533, val = 0.1531
 Model 19: $y(k-1) u(k-6)$, Error: trn = 0.1952, val = 0.1853
 Currently selected inputs: $y(k-1) u(k-4)$

Selecting input 3 ...

Model 20: $y(k-1) u(k-4) y(k-2)$, Error: trn = 0.0808, val = 0.0822
 Model 21: $y(k-1) u(k-4) y(k-3)$, Error: trn = 0.0806, val = 0.0836
 Model 22: $y(k-1) u(k-4) y(k-4)$, Error: trn = 0.0817, val = 0.0855
 Model 23: $y(k-1) u(k-4) u(k-1)$, Error: trn = 0.0886, val = 0.0912
 Model 24: $y(k-1) u(k-4) u(k-2)$, Error: trn = 0.0835, val = 0.0843
 Model 25: $y(k-1) u(k-4) u(k-3)$, Error: trn = 0.0609, val = 0.0604
 Model 26: $y(k-1) u(k-4) u(k-5)$, Error: trn = 0.0848, val = 0.0867
 Model 27: $y(k-1) u(k-4) u(k-6)$, Error: trn = 0.0890, val = 0.0894
 Currently selected inputs: $y(k-1) u(k-3) u(k-4)$



This plot shows all combinations of inputs tried by `sequentialSearch`. The search selects $y(k-1)$, $u(k-3)$, and $u(k-4)$ as inputs since the model with these inputs has the lowest training RMSE and validation RMSE.

Alternatively, you can use an exhaustive search on all possible combinations of the input candidates. As before, search for three inputs out of the 10 candidates. You can use the function `exhaustiveSearch` for such a search; however, this function tries all possible combinations of candidates, $\binom{10}{3} = 120$ in this case.

Instead of `exhaustiveSearch`, use custom code to search through a subset of these combinations. For this example, do not select any input combination exclusively from the inputs or exclusively from the outputs.

As a reasonable guess, select input combinations with two output values and one input value, which produces 36 possible input combinations. Define groups for selecting input indices: two groups for selecting an output and one group for selecting an input.

```
group1 = [1 2 3 4]; % y(k-1), y(k-2), y(k-3), y(k-4)
group2 = [1 2 3 4]; % y(k-1), y(k-2), y(k-3), y(k-4)
group3 = [5 6 7 8 9 10]; % u(k-1) through u(k-6)
```

Specify parameters and options for training.

```
anfis_n = 6*length(group3);
index = zeros(anfis_n,3);
trn_error = zeros(anfis_n,1);
val_error = zeros(anfis_n,1);

% Create option set for generating initial FIS.
genOpt = genfisOptions("GridPartition","NumMembershipFunctions",2, ...
    "InputMembershipFunctionType","gbellmf");
% Create option set for anfis function and set options that remain
% constant for different training scenarios.
anfisOpt = anfisOptions("EpochNumber",1,...
    "InitialStepSize",0.1,...
    "StepSizeDecreaseRate",0.5,...
    "StepSizeIncreaseRate",1.5,...
    "DisplayANFISInformation",0,...
    "DisplayErrorValues",0,...
    "DisplayStepSize",0,...
    "DisplayFinalResults",0);
```

Train ANFIS model for each input combination.

```
model = 1;
for i = 1:length(group1)
    for j = i+1:length(group2)
        for k = 1:length(group3)
            % Create input combinations.
            in1 = input_name(group1(i));
            in2 = input_name(group2(j));
            in3 = input_name(group3(k));
            index(model, :) = [group1(i) group2(j) group3(k)];
            trn_data = data(1:trn_data_n, ...
                [group1(i) group2(j) group3(k) size(data,2)]);
            val_data = data(trn_data_n+1:trn_data_n+300, ...
```



```

        [group1(i) group2(j) group3(k) size(data,2)];

% Create the initial FIS structure.
in_fis = genfis(trn_data(:,1:end-1),trn_data(:,end),genOpt);

% Set the initial FIS and validation data for ANFIS training.
anfisoOpt.InitialFIS = in_fis;
anfisoOpt.ValidationData = val_data;

% Train the ANFIS system.
[~,t_err,~,~,c_err] = anfis(trn_data,anfisoOpt);
trn_error(model) = min(t_err);
val_error(model) = min(c_err);
model = model+1;
    end
end
end
end

```

Plot the training and validation errors for each input combination in decreasing order.


```

% Reorder according to training error.
[~, b] = sort(trn_error);
b = flipud(b);
trn_error = trn_error(b);
val_error = val_error(b);
index = index(b,:);

% Plot training and validation error.
x = (1:anfiso_n)';
tmp = x(:, ones(1,3))';
X = tmp(:);
tmp = [zeros(anfiso_n,1) max(trn_error,val_error) nan*ones(anfiso_n,1)]';
Y = tmp(:);
figure
plot(x,trn_error,"-o",x,val_error,"-*",X,Y,"g")
title("Error for Corresponding Inputs")
ylabel("RMSE")
legend("Training","Validation","Location","northeast")

% Add ticks and labels.
labels = string(zeros(anfiso_n,1));
for k = 1:anfiso_n
    labels(k) = input_name(index(k,1))+ " & " + ...
                input_name(index(k,2))+ " & " + ...
                input_name(index(k,3));
end
xticks(x)
xticklabels(labels)
xtickangle(90)

```



The algorithm selects the inputs $y(k - 1)$, $y(k - 2)$, and $u(k - 3)$ with a training RMSE of 0.0474 and a validation RMSE of 0.0485. These RMSE values improve on those of the ARX models and that of the ANFIS model found by sequential forward search.

Compute and plot the ANFIS predictions for both the training and validation data sets using the selected input combination.

To do so, first generate the data set.

```
[~,b] = min(trn_error);
input_index = index(b,:);
trn_data = data(1:trn_data_n,[input_index, size(data,2)]);
val_data = data(trn_data_n+1:600,[input_index, size(data,2)]);
```

Create and train the ANFIS.

```
in_fis = genfis(trn_data(:,1:end-1),trn_data(:,end));
anfisopt = anfisOptions("InitialFIS",in_fis,...
    "EpochNumber",1,...
    "InitialStepSize",0.01,...
    "StepSizeDecreaseRate",0.5,...
    "StepSizeIncreaseRate",1.5,...
    "ValidationData",val_data);
[trn_out_fis,trn_error,step_size,val_out_fis,val_error] = ...
    anfis(trn_data,anfisopt);
```

ANFIS info:
Number of nodes: 34

```

Number of linear parameters: 32
Number of nonlinear parameters: 18
Total number of parameters: 50
Number of training data pairs: 300
Number of checking data pairs: 300
Number of fuzzy rules: 8

```

```
Start training ANFIS ...
```

```
1      0.0474113      0.0485325
```

```
Designated epoch number reached. ANFIS training completed at epoch 1.
```

```
Minimal training RMSE = 0.0474113
```

```
Minimal checking RMSE = 0.0485325
```

```
Evaluate the FIS for which the validation error is minimum.
```


```
y_hat = evalfis(val_out_fis,data(1:600,input_index));
```

```

figure
subplot(2,1,1)
index = 1:trn_data_n;
plot(index,data(index,size(data,2)),'-', ...
      index,y_hat(index),'.')
rmse = norm(y_hat(index)-data(index,size(data,2)))/sqrt(length(index));
title("Training Data (solid), ANFIS Prediction (dots)" ...
      + newline + "RMSE = " + num2str(rmse))
xlabel("Time Steps")

subplot(2,1,2)
index = trn_data_n+1:600;
plot(index,data(index,size(data,2)),'-',index,y_hat(index),'.')
rmse = norm(y_hat(index)-data(index,size(data,2)))/sqrt(length(index));
title("Validation Data (solid), ANFIS Prediction (dots)" ...
      + newline + "RMSE = " + num2str(rmse))
xlabel("Time Steps")

```



The ANFIS model predictions fit the data much more closely than the ARX model predictions.

Reference

[1] Ljung, Lennart. *System Identification: Theory for the User*. Prentice-Hall Information and System Sciences Series. Englewood Cliffs, NJ: Prentice-Hall, 1987.

See Also

`anfis` | `genfis` | `evalfis`

More About

- “Neuro-Adaptive Learning and ANFIS” on page 3-171

Gas Mileage Prediction

This example shows how to predict fuel consumption for automobiles using data from previously recorded observations.

Automobile miles per gallon (MPG) prediction is a typical nonlinear regression problem, in which several automobile features are used to predict fuel consumption in MPG. The training data for this example is available in the University of California, Irvine Machine Learning Repository and contains data collected from automobiles of various makes and models.

In this data set, the six input variables are number of cylinders, displacement, horsepower, weight, acceleration, and model year. The output variable to predict is the fuel consumption in MPG. In this example, you do not use the make and model information from the data set.

Partition Data

Obtain the data set from the original data file `auto-gas.dat` using the `loadGasData` function.

```
[data,input_name] = loadGasData;
```

Partition the dataset into a training set (odd-indexed samples) and a validation set (even-indexed samples).

```
trn_data = data(1:2:end,:);  
val_data = data(2:2:end,:);
```


Select Inputs

Use the `exhaustiveSearch` function to perform an exhaustive search within the available inputs to select the set of inputs that most influence the fuel consumption. Use the first argument of `exhaustiveSearch` to specify the number of inputs per combination (1 for this example). `exhaustiveSearch` builds an ANFIS model for each combination, trains it for one epoch, and reports the performance achieved. First, use `exhaustiveSearch` to determine which variable by itself can best predict the output.

```
exhaustiveSearch(1,trn_data,val_data,input_name);
```

Train 6 ANFIS models, each with 1 inputs selected from 6 candidates...

```
Model 1: Cylinder, Error: trn = 4.6400, val = 4.7255  
Model 2: Disp, Error: trn = 4.3106, val = 4.4316  
Model 3: Power, Error: trn = 4.5399, val = 4.1713  
Model 4: Weight, Error: trn = 4.2577, val = 4.0863  
Model 5: Acceler, Error: trn = 6.9789, val = 6.9317  
Model 6: Year, Error: trn = 6.2255, val = 6.1693
```



The graph indicates that the Weight variable has the least root mean squared error. In other words, it can best predict MPG.

For Weight, the training and validation errors are comparable, indicating little overfitting. Therefore, you can likely use more than one input variable in your ANFIS model.


Although models using Weight and Disp individually have the lowest errors, a combination of these two variables does not necessarily produce the minimal training error. To identify which combination of two input variables results in the lowest error, use `exhaustiveSearch` to search every combination.

```
input_index = exhaustiveSearch(2, trn_data, val_data, input_name);
```

Train 15 ANFIS models, each with 2 inputs selected from 6 candidates...

```
ANFIS model 1: Cylinder Disp, Error: trn = 3.9320, val = 4.7920
ANFIS model 2: Cylinder Power, Error: trn = 3.7364, val = 4.8683
ANFIS model 3: Cylinder Weight, Error: trn = 3.8741, val = 4.6763
ANFIS model 4: Cylinder Acceler, Error: trn = 4.3287, val = 5.9625
ANFIS model 5: Cylinder Year, Error: trn = 3.7129, val = 4.5946
ANFIS model 6: Disp Power, Error: trn = 3.8087, val = 3.8594
ANFIS model 7: Disp Weight, Error: trn = 4.0271, val = 4.6351
ANFIS model 8: Disp Acceler, Error: trn = 4.0782, val = 4.4890
ANFIS model 9: Disp Year, Error: trn = 2.9565, val = 3.3905
ANFIS model 10: Power Weight, Error: trn = 3.9310, val = 4.2983
ANFIS model 11: Power Acceler, Error: trn = 4.2740, val = 3.8738
ANFIS model 12: Power Year, Error: trn = 3.3796, val = 3.3505
```

ANFIS model 13: Weight Acceler, Error: trn = 4.0875, val = 4.0095
 ANFIS model 14: Weight Year, Error: trn = 2.7657, val = 2.9954
 ANFIS model 15: Acceler Year, Error: trn = 5.6242, val = 5.6481




The results from exhaustiveSearch indicate that Weight and Year form the optimal combination of two input variables. However, the difference between the training and validation errors is larger than the difference for either variable alone, indicating that including more variables increases overfitting. Run exhaustiveSearch with combinations of three input variables to see whether these differences increase further with greater model complexity.

```
exhaustiveSearch(3, trn_data, val_data, input_name);
```

Train 20 ANFIS models, each with 3 inputs selected from 6 candidates...

```
ANFIS model 1: Cylinder Disp Power, Error: trn = 3.4446, val = 11.5329
ANFIS model 2: Cylinder Disp Weight, Error: trn = 3.6686, val = 4.8923
ANFIS model 3: Cylinder Disp Acceler, Error: trn = 3.6610, val = 5.2384
ANFIS model 4: Cylinder Disp Year, Error: trn = 2.5463, val = 4.9001
ANFIS model 5: Cylinder Power Weight, Error: trn = 3.4797, val = 9.3759
ANFIS model 6: Cylinder Power Acceler, Error: trn = 3.5432, val = 4.4804
ANFIS model 7: Cylinder Power Year, Error: trn = 2.6300, val = 3.6300
ANFIS model 8: Cylinder Weight Acceler, Error: trn = 3.5708, val = 4.8380
ANFIS model 9: Cylinder Weight Year, Error: trn = 2.4951, val = 4.0433
ANFIS model 10: Cylinder Acceler Year, Error: trn = 3.2698, val = 6.2616
ANFIS model 11: Disp Power Weight, Error: trn = 3.5879, val = 7.4978
ANFIS model 12: Disp Power Acceler, Error: trn = 3.5395, val = 3.9953
ANFIS model 13: Disp Power Year, Error: trn = 2.4607, val = 3.3563
```

ANFIS model 14: Disp Weight Acceler, Error: trn = 3.6075, val = 4.2326
 ANFIS model 15: Disp Weight Year, Error: trn = 2.5617, val = 3.7855
 ANFIS model 16: Disp Acceler Year, Error: trn = 2.4149, val = 3.2480
 ANFIS model 17: Power Weight Acceler, Error: trn = 3.7884, val = 4.0476
 ANFIS model 18: Power Weight Year, Error: trn = 2.4371, val = 3.2866
 ANFIS model 19: Power Acceler Year, Error: trn = 2.7276, val = 3.2580
 ANFIS model 20: Weight Acceler Year, Error: trn = 2.3603, val = 2.9152



This plot shows the result of selecting three inputs. Here, the combination of `Weight`, `Year`, and `Acceler` produces the lowest training error. However, the training and validation errors are not substantially lower than that of the best two-input model, which indicates that the newly added variable `Acceler` does not improve the prediction much. As simpler models usually generalize better, use the two-input ANFIS for further exploration.

Extract the selected input variables from the original training and validation data sets.

```
new_trn_data = trn_data(:,[input_index, size(trn_data,2)]);
new_val_data = val_data(:,[input_index, size(val_data,2)]);
```

Train ANFIS Model

The function `exhaustiveSearch` trains each ANFIS for only a single epoch to quickly find the right inputs. Now that the inputs are fixed, you can train the ANFIS model for more epochs.

Use the `genfis` function to generate an initial FIS from the training data, then use `anfis` to fine-tune it.


```

in_fis = genfis(new_trn_data(:,1:end-1),new_trn_data(:,end));
anfisOpt = anfisOptions('InitialFIS',in_fis,'EpochNumber',100,...
    'StepSizeDecreaseRate',0.5,...
    'StepSizeIncreaseRate',1.5,...
    'ValidationData',new_val_data,...
    'DisplayANFISInformation',0,...
    'DisplayErrorValues',0,...
    'DisplayStepSize',0,...
    'DisplayFinalResults',0);
[trn_out_fis,trn_error,step_size,val_out_fis,val_error] = ...
    anfis(new_trn_data,anfisOpt);

```

anfis returns the training and validation errors. Plot the training and validation errors over the course of the training process.

```

[a,b] = min(val_error);
plot(1:100,trn_error,'g-',1:100,val_error,'r-',b,a,'ko')
title('Training (green) and validation (red) error curve')
xlabel('Epoch number')
ylabel('RMSE')

```



This plot shows the error curves for 100 epochs of ANFIS training. The green curve gives the training errors and the red curve gives the validation errors. The minimal validation error occurs at about epoch 45, which is indicated by a circle. Notice that the validation error curve goes up after 50 epochs, indicating that further training overfits the data and produces increasingly worse generalization.

Analyze ANFIS Model

First, compare the performance of the ANFIS model with that of a linear model using their respective validation RMSE values.

The ANFIS prediction can be compared against a linear regression model by comparing their respective RMSE (Root mean square) values against validation data.

```
% Perform linear regression
N = size(trn_data,1);
A = [trn_data(:,1:6) ones(N,1)];
B = trn_data(:,7);
coef = A\B; % Solve for regression parameters from training data

Nc = size(val_data,1);
A_ck = [val_data(:,1:6) ones(Nc,1)];
B_ck = val_data(:,7);
lr_rmse = norm(A_ck*coef-B_ck)/sqrt(Nc);

fprintf('\nRMSE against validation data\nANFIS : %1.3f\tLinear Regression : %1.3f\n',...
        a,lr_rmse);
```


```
RMSE against validation data
ANFIS : 2.978    Linear Regression : 3.444
```

The ANFIS model has a lower validation RMSE and therefore outperforms the linear regression model.

The variable `val_out_fis` is a snapshot of the ANFIS model at the minimal validation error during the training process. Plot an output surface of the model.

```
val_out_fis.Inputs(1).Name = "Weight";
val_out_fis.Inputs(2).Name = "Year";
val_out_fis.Outputs(1).Name = "MPG";


gensurf(val_out_fis)
```



The output surface is nonlinear and monotonic and illustrates how the ANFIS model responds to varying values of Weight and Year.

The surface indicates that, for vehicles manufactured in or after 1978, heavier automobiles are more efficient. Plot the data distribution to see any potential gaps in the input data that might cause this counterintuitive result.

```
plot(new_trn_data(:,1),new_trn_data(:,2),'bo', ...  
     new_val_data(:,1),new_val_data(:,2),'rx')  
xlabel('Weight')  
ylabel('Year')  
title('Training (o) and Validation (x) Data')
```



The lack of training data for heavier vehicles manufactured in later years causes the anomalous results. Because data distribution strongly affects prediction accuracy, take the data distribution into account when you interpret the ANFIS model.

See Also

`anfis` | `genfis` | `evalfis`

More About

- “Neuro-Adaptive Learning and ANFIS” on page 3-171

Data Clustering

- “Fuzzy Clustering” on page 4-2
- “Cluster Quasi-Random Data Using Fuzzy C-Means Clustering” on page 4-4
- “Adjust Fuzzy Overlap in Fuzzy C-Means Clustering” on page 4-7
- “Fuzzy C-Means Clustering” on page 4-9
- “Fuzzy C-Means Clustering for Iris Data” on page 4-13
- “Model Suburban Commuting Using Subtractive Clustering and ANFIS” on page 4-17
- “Cluster Data Using Clustering Tool” on page 4-29

Fuzzy Clustering

What Is Data Clustering?

Clustering of numerical data forms the basis of many classification and system modeling algorithms. The purpose of clustering is to identify natural groupings of data from a large data set to produce a concise representation of a system's behavior.

Fuzzy Logic Toolbox tools allow you to find clusters in input-output training data. You can use the cluster information to generate a Sugeno-type fuzzy inference system that best models the data behavior using a minimum number of rules. The rules partition themselves according to the fuzzy qualities associated with each of the data clusters. To automatically generate this type of FIS, use the `genfis` command.

Fuzzy C-Means Clustering

Fuzzy c-means (FCM) is a data clustering technique wherein each data point belongs to a cluster to some degree that is specified by a membership grade. This technique was originally introduced by Jim Bezdek in 1981 [1] as an improvement on earlier clustering methods. It provides a method that shows how to group data points that populate some multidimensional space into a specific number of different clusters.

The command line function `fcm` starts with an initial guess for the cluster centers, which are intended to mark the mean location of each cluster. The initial guess for these cluster centers is most likely incorrect. Additionally, `fcm` assigns every data point a membership grade for each cluster. By iteratively updating the cluster centers and the membership grades for each data point, `fcm` iteratively moves the cluster centers to the right location within a data set. This iteration is based on minimizing an objective function that represents the distance from any given data point to a cluster center weighted by that data point's membership grade.

The command line function `fcm` outputs a list of cluster centers and several membership grades for each data point. You can use the information returned by `fcm` to help you build a fuzzy inference system by creating membership functions to represent the fuzzy qualities of each cluster. To generate a Sugeno-type fuzzy inference system that models the behavior of input/output data, you can configure the `genfis` command to use FCM clustering.

Subtractive Clustering

If you do not have a clear idea how many clusters there should be for a given set of data, *subtractive clustering* is a fast, one-pass algorithm for estimating the number of clusters and the cluster centers for a set of data [2]. The cluster estimates, which are obtained from the `subclust` function, can be used to initialize iterative optimization-based clustering methods (`fcm`) and model identification methods (like `anfis`). The `subclust` function finds the clusters using the subtractive clustering method.

To generate a Sugeno-type fuzzy inference system that models the behavior of input/output data, you can configure the `genfis` command to use subtractive clustering.

References

- [1] Bezdek, J.C., *Pattern Recognition with Fuzzy Objective Function Algorithms*, Plenum Press, New York, 1981.
- [2] Chiu, S., "Fuzzy Model Identification Based on Cluster Estimation," *Journal of Intelligent & Fuzzy Systems*, Vol. 2, No. 3, Sept. 1994.

See Also

fcm | subclust | genfis

More About


- "Cluster Quasi-Random Data Using Fuzzy C-Means Clustering" on page 4-4
- "Model Suburban Commuting Using Subtractive Clustering and ANFIS" on page 4-17
- "Cluster Data Using Clustering Tool" on page 4-29

Cluster Quasi-Random Data Using Fuzzy C-Means Clustering

This example shows how FCM clustering works using quasi-random two-dimensional data.

Load the data set and plot it.

```
load fcmdata.dat
plot(fcmdata(:,1), fcmdata(:,2), 'o')
```



Next, invoke the command-line function, `fcm`, to find two clusters in this data set until the objective function is no longer decreasing much at all.

```
[center,U,objFcn] = fcm(fcmdata,2);
```

```
Iteration count = 1, obj. fcn = 8.970479
Iteration count = 2, obj. fcn = 7.197402
Iteration count = 3, obj. fcn = 6.325579
Iteration count = 4, obj. fcn = 4.586142
Iteration count = 5, obj. fcn = 3.893114
Iteration count = 6, obj. fcn = 3.810804
Iteration count = 7, obj. fcn = 3.799801
Iteration count = 8, obj. fcn = 3.797862
Iteration count = 9, obj. fcn = 3.797508
Iteration count = 10, obj. fcn = 3.797444
Iteration count = 11, obj. fcn = 3.797432
Iteration count = 12, obj. fcn = 3.797430
```



center contains the coordinates of the two cluster centers, U contains the membership grades for each of the data points, and objFcn contains a history of the objective function across the iterations.

The fcm function is an iteration loop built on top of the following routines:

- `initfcm` - initializes the problem
- `distfcm` - performs Euclidean distance calculation
- `stepfcm` - performs one iteration of clustering

To view the progress of the clustering, plot the objective function.


```
figure
plot(objFcn)
title('Objective Function Values')
xlabel('Iteration Count')
ylabel('Objective Function Value')
```



Finally, plot the two cluster centers found by the fcm function. The large characters in the plot indicate cluster centers.

```
maxU = max(U);
index1 = find(U(1,:) == maxU);
index2 = find(U(2,:) == maxU);
figure
line(fcmdata(index1,1), fcmdata(index1,2), 'linestyle',...
      'none','marker', 'o','color','g')
line(fcmdata(index2,1), fcmdata(index2,2), 'linestyle',...
```

```
                                'none','marker', 'x','color','r')
hold on
plot(center(1,1),center(1,2),'ko','markersize',15,'LineWidth',2)
plot(center(2,1),center(2,2),'kx','markersize',15,'LineWidth',2)
```



Note: Every time you run this example, the `fcm` function initializes with different initial conditions. This behavior swaps the order in which the cluster centers are computed and plotted.

See Also

`fcm`

More About

- “Fuzzy Clustering” on page 4-2

Adjust Fuzzy Overlap in Fuzzy C-Means Clustering

This example shows how to adjust the amount of fuzzy overlap when performing fuzzy c-means clustering.

Create a random data set. For reproducibility, initialize the random number generator to its default value.

```
rng('default')
data = rand(100,2);
```

Specify fuzzy partition matrix exponents.

```
M = [1.1 2.0 3.0 4.0];
```

The exponent values in M must be greater than 1, with smaller values specifying a lower degree of fuzzy overlap. In other words, as M approaches 1, the boundaries between the clusters become more crisp.

For each overlap exponent:

- Cluster the data.
- Classify each data point into the cluster for which it has the highest degree of membership.
- Find the data points with maximum membership values below 0.6. These points have a more fuzzy classification.
- To quantify the degree of fuzzy overlap, calculate the average maximum membership value across all data points. A higher average maximum membership value indicates that there is less fuzzy overlap.
- Plot the clustering results.

```
for i = 1:4
    % Cluster the data.
    options = [M(i) NaN NaN 0];
    [centers,U] = fcm(data,2,options);

    % Classify the data points.
    maxU = max(U);
    index1 = find(U(1,:) == maxU);
    index2 = find(U(2,:) == maxU);

    % Find data points with lower maximum membership values.
    index3 = find(maxU < 0.6);


    % Calculate the average maximum membership value.
    averageMax = mean(maxU);

    % Plot the results.
    subplot(2,2,i)
    plot(data(index1,1),data(index1,2),'ob')
    hold on
    plot(data(index2,1),data(index2,2),'or')
    plot(data(index3,1),data(index3,2),'xk','LineWidth',2)
    plot(centers(1,1),centers(1,2),'xb','MarkerSize',15,'LineWidth',3)
    plot(centers(2,1),centers(2,2),'xr','MarkerSize',15,'LineWidth',3)
    hold off
```

```

title(['M = ' num2str(M(i)) ', Ave. Max. = ' num2str(averageMax,3)])
end

```



A given data point is classified into the cluster for which it has the highest membership value, as indicated by $\max U$. A maximum membership value of 0.5 indicates that the point belongs to both clusters equally. The data points marked with a black x have maximum membership values below 0.6. These points have a greater degree of uncertainty in their cluster membership.

More data points with low maximum membership values indicate a greater degree of fuzzy overlap in the clustering result. The average maximum membership value, averageMax , provides a quantitative description of the overlap. An averageMax value of 1 indicates crisp clusters, with smaller values indicating more overlap.

See Also

fcm

More About

- “Fuzzy Clustering” on page 4-2
- “Cluster Quasi-Random Data Using Fuzzy C-Means Clustering” on page 4-4

Fuzzy C-Means Clustering

This example shows how to perform fuzzy c-means clustering on 2-dimensional data. For an example that clusters higher-dimensional data, see “Fuzzy C-Means Clustering for Iris Data” on page 4-13.

Fuzzy c-means (FCM) is a data clustering technique in which a data set is grouped into N clusters with every data point in the dataset belonging to every cluster to a certain degree. For example, a data point that lies close to the center of a cluster will have a high degree of membership in that cluster, and another data point that lies far away from the center of a cluster will have a low degree of membership to that cluster.

The `fcm` function performs FCM clustering. It starts with a random initial guess for the cluster centers; that is the mean location of each cluster. Next, `fcm` assigns every data point a random membership grade for each cluster. By iteratively updating the cluster centers and the membership grades for each data point, `fcm` moves the cluster centers to the correct location within a data set and, for each data point, finds the degree of membership in each cluster. This iteration minimizes an objective function that represents the distance from any given data point to a cluster center weighted by the membership of that data point in the cluster.

Load Data

Load the five sample data sets, and select a data set to cluster. These data sets have different numbers of clusters and data distributions.

```
load fcmdata
dataset =  ;
```

Specify FCM Settings

Configure the clustering algorithm settings. For more information on these settings, see `fcm`. To obtain accurate clustering results for each data set, try different clustering options.

Specify the number of clusters to compute, which must be greater than 1.

```
N = 4  ;
```

Specify the exponent the fuzzy partition matrix, which controls the degree of fuzzy overlap between clusters. This value must be greater than 1, with smaller values creating more crisp cluster boundaries. For more information, see “Adjust Fuzzy Overlap in Fuzzy C-Means Clustering” on page 4-7.

```
exp = 2  ;
```

Specify the maximum number of optimization iterations.

```
maxIter = 100  ;
```

Specify the minimum improvement in the objective function between successive iterations. When the objective function improves by a value below this threshold, the optimization stops. A smaller value produces more accurate clustering results, but the clustering can take longer to converge.

```
minImprove = 0.00001  ;
```

Specify whether to display the objective function value after each iteration.

```
displayObjective = ;
```

Create an option vector for the fcm function using these settings.

```
options = [exp maxIter minImprove displayObjective];
```

Cluster Data

Cluster the data into N clusters.

```
[C,U] = fcm(dataset,N,options);
```

C contains the computed centers for each cluster. U contains the computed fuzzy partition matrix, which indicates the degree of membership of each data point within each cluster.


Classify each data point into the cluster for which it has the highest degree of membership.

```
maxU = max(U);  
index = cell(N,1);  
for i=1:N  
    index{i} = find(U(i,:) == maxU);  
end
```

Plot Clustering Results

Plot the clustering results.

```
figure  
hold on  
for i=1:N  
    plot(dataset(index{i},1),dataset(index{i},2),'o')  
    plot(C(i,1),C(i,2),'xk','MarkerSize',15,'LineWidth',3)  
end  
hold off
```



The data points in each cluster are shown in a different colors. The center for each cluster is shown as a black X.


Plot Data Point Membership Values

Select a cluster for which to plot a membership function surface.

cluster = 2 _____ ;

Obtain the membership function for the selected cluster by fitting a surface to the cluster membership values for all data points. For more information on interpolating scattered 3-D data, see `griddata`.

```
[X,Y] = meshgrid(0:0.05:1, 0:0.05:1);
Z = griddata(dataset(:,1),dataset(:,2),U(cluster,:),X,Y);
surf(X,Y,Z)
```



When you decrease the exponent value, the transition from maximum full cluster membership to zero cluster membership becomes more steep; that is, the cluster boundary becomes more crisp.

See Also

fcm

More About

- “Fuzzy Clustering” on page 4-2

Fuzzy C-Means Clustering for Iris Data

This example shows how to use fuzzy c-means clustering for the iris data set. This dataset was collected by botanist Edgar Anderson and contains random samples of flowers belonging to three species of iris flowers: *setosa*, *versicolor*, and *virginica*. For each of the species, the data set contains 50 observations for sepal length, sepal width, petal length, and petal width.

Load Data

Load the data set from the `iris.dat` data file.

```
load iris.dat
```

Partition the data into three groups named `setosa`, `versicolor`, and `virginica`.

```
setosaIndex = iris(:,5)==1;
versicolorIndex = iris(:,5)==2;
virginicaIndex = iris(:,5)==3;


setosa = iris(setosaIndex,:);
versicolor = iris(versicolorIndex,:);
virginica = iris(virginicaIndex,:);
```

Plot Data in 2-D

The iris data contains four dimensions representing sepal length, sepal width, petal length, and petal width. Plot the data points for each combination of two dimensions.

```
Characteristics = {'sepal length', 'sepal width', ...
                  'petal length', 'petal width'};
pairs = [1 2; 1 3; 1 4; 2 3; 2 4; 3 4];

for i = 1:6
    x = pairs(i,1);
    y = pairs(i,2);
    subplot(2,3,i)
    plot([setosa(:,x) versicolor(:,x) virginica(:,x)], ...
         [setosa(:,y) versicolor(:,y) virginica(:,y)]], '.')
    xlabel(Characteristics{x})
    ylabel(Characteristics{y})
end
```



Setup Parameters

Specify the options for clustering the data using fuzzy c-means clustering. These options are:

- `Nc` — Number of clusters
- `M` — Fuzzy partition matrix exponent, which indicates the degree of fuzzy overlap between clusters. For more information, see “Adjust Fuzzy Overlap in Fuzzy C-Means Clustering” on page 4-7.
- `maxIter` — Maximum number of iterations. The clustering process stops after this number of iterations.
- `minImprove` — Minimum improvement. The clustering process stops when the objective function improvement between two consecutive iterations is less than this value.

```
Nc = 3;
M = 2.0;
maxIter = 100;
minImprove = 1e-6;
```

For more information about these options and the fuzzy c-means algorithm, see `fcm`.

Compute Clusters

Fuzzy c-means clustering is an iterative process. Initially, the `fcm` function generates a random fuzzy partition matrix. This matrix indicates the degree of membership of each data point in each cluster.

In each clustering iteration, `fcm` calculates the cluster centers and updates the fuzzy partition matrix using the calculated center locations. It then computes the objective function value.

Cluster the data, displaying the objective function value after each iteration.


```
clusteringOptions = [M maxIter minImprove true];
[centers,U] = fcm(iris,Nc,clusteringOptions);
```

```
Iteration count = 1, obj. fcn = 28838.424340
Iteration count = 2, obj. fcn = 21010.880067
Iteration count = 3, obj. fcn = 15272.280943
Iteration count = 4, obj. fcn = 11029.756194
Iteration count = 5, obj. fcn = 10550.015503
Iteration count = 6, obj. fcn = 10301.776800
Iteration count = 7, obj. fcn = 9283.793786
Iteration count = 8, obj. fcn = 7344.379868
Iteration count = 9, obj. fcn = 6575.117093
Iteration count = 10, obj. fcn = 6295.215539
Iteration count = 11, obj. fcn = 6167.772051
Iteration count = 12, obj. fcn = 6107.998500
Iteration count = 13, obj. fcn = 6080.461019
Iteration count = 14, obj. fcn = 6068.116247
Iteration count = 15, obj. fcn = 6062.713326
Iteration count = 16, obj. fcn = 6060.390433
Iteration count = 17, obj. fcn = 6059.403978
Iteration count = 18, obj. fcn = 6058.988494
Iteration count = 19, obj. fcn = 6058.814438
Iteration count = 20, obj. fcn = 6058.741777
Iteration count = 21, obj. fcn = 6058.711512
Iteration count = 22, obj. fcn = 6058.698925
Iteration count = 23, obj. fcn = 6058.693695
Iteration count = 24, obj. fcn = 6058.691523
Iteration count = 25, obj. fcn = 6058.690622
Iteration count = 26, obj. fcn = 6058.690247
Iteration count = 27, obj. fcn = 6058.690092
Iteration count = 28, obj. fcn = 6058.690028
Iteration count = 29, obj. fcn = 6058.690001
Iteration count = 30, obj. fcn = 6058.689990
Iteration count = 31, obj. fcn = 6058.689985
Iteration count = 32, obj. fcn = 6058.689983
Iteration count = 33, obj. fcn = 6058.689983
```

The clustering stops when the objective function improvement is below the specified minimum threshold.

Plot the computed cluster centers as bold numbers.

```
for i = 1:6
    subplot(2,3,i)
    for j = 1:Nc
        x = pairs(i,1);
        y = pairs(i,2);
        text(centers(j,x),centers(j,y),int2str(j),...
            'FontWeight','bold');
    end
end
```



See Also

fcm

More About

- “Fuzzy Clustering” on page 4-2

Model Suburban Commuting Using Subtractive Clustering and ANFIS

This example shows how to model the relationship between the number of automobile trips generated from an area and the demographics of the area using subtractive clustering and ANFIS tuning.

Load Traffic Data

This example uses demographic and trip data from 100 traffic analysis zones in New Castle County, Delaware. The data set contains five demographic factors as input variables: population, number of dwelling units, vehicle ownership, median household income, and total employment. The data contains one output variable, number of automobile trips.

Load the training and validation data.


```
load trafficData
```

The data set contains 100 data points, 75 for training and 25 for validation. The training input data (`datain`) and validation input data (`valdatain`) each have five columns that represent the input variables. The training output data (`dataout`) and validation output data (`valdataout`) each have one column that represents the output variable.

Plot the training data.

```
subplot(2,1,1)
plot(datain)
legend("population","number of dwellings","vehicle ownership",...
      "median income","total employment","Location","northwest")
title('Input Variables')
xlabel('Data Point')

subplot(2,1,2)
plot(dataout)
legend("number of trips")
title("Output Variable")
xlabel('Data Point')
```



Cluster Data

Subtractive clustering is a fast one-pass algorithm for estimating the number of clusters and the cluster centers in a data set. To cluster the training data using subtractive clustering, use the `subclust` function.

```
[C,S] = subclust([datain dataout],0.5);
```

For this example, use a cluster influence range of 0.5. This value indicates the range of influence of a cluster when you consider the data space as a unit hypercube. Specifying a small cluster radius usually generates many small clusters in the data, which produces a FIS with many rules. Specifying a large cluster radius usually produces a few large clusters in the data and results in fewer rules.

Each row of `C` contains the position of a cluster center identified by the clustering algorithm. In this case, the algorithm found three clusters in the data.

`C`

```
C = 3x6
```


1.8770	0.7630	0.9170	18.7500	1.5650	2.1830
0.3980	0.1510	0.1320	8.1590	0.6250	0.6480
3.1160	1.1930	1.4870	19.7330	0.6030	2.3850

Plot the training data along with the cluster centers for two of the input variables.

```

figure
plot(datain(:,5),dataout(:,1),'.','r*',C(:,5),C(:,6),"r*")
legend("Data points","Cluster centers","Location","southeast")
xlabel("Total Employment")
ylabel("Number of Trips")
title("Data and Cluster Centers")

```



The values in S show the range of influence of the cluster centers for each data dimension. All cluster centers have the same set of S values.

S

$S = 1 \times 6$

1.1621 0.4117 0.6555 7.6139 2.8931 1.4395

Generate Fuzzy Inference System Using Data Clusters

Use the `genfis` function to generate a fuzzy inference system (FIS) from the data using subtractive clustering.

An important advantage of using a clustering method to find rules is that the resultant rules are more tailored to the input data than they are in a FIS generated without clustering. This tailoring reduces the total number of rules when the input data has a high dimension.

First, create a `genfisOptions` option set for subtractive clustering, specifying the same cluster influence range value.

```
fisOpt = genfisOptions("SubtractiveClustering",...  
    "ClusterInfluenceRange",0.5);
```

Generate the FIS model using the training data and the specified options.

```
fis = genfis(datain,dataout,fisOpt);
```

Based on the dimensions of the input and output training data, the generated FIS has five inputs and one output. `genfis` assigns default names for inputs, outputs, and membership functions.

The generated FIS object is a first-order Sugeno system with three rules.

```
showrule(fis,"Format","symbolic")
```


```
ans = 3x132 char array
```

```
'1. (in1==in1cluster1) & (in2==in2cluster1) & (in3==in3cluster1) & (in4==in4cluster1) & (in5-  
'2. (in1==in1cluster2) & (in2==in2cluster2) & (in3==in3cluster2) & (in4==in4cluster2) & (in5-  
'3. (in1==in1cluster3) & (in2==in2cluster3) & (in3==in3cluster3) & (in4==in4cluster3) & (in5-
```

You can conceptualize each rule as follows: If the inputs to the FIS (population, dwelling units, num vehicles, income, and employment) strongly belong to their representative membership functions for a cluster, then the output (num of trips) must belong to the same cluster. That is, each rule succinctly maps a cluster in the input space to the same cluster in the output space.

Each input and output variable has three membership functions, which correspond to the three identified clusters. The parameters of the input and output membership functions are derived based on the cluster centers and cluster ranges of influence. As an example, plot the membership functions for the first input variable.

```
figure  
plotmf(fis,"input",1)
```

Evaluate Initial FIS Performance

Apply the training input values to the fuzzy system and find corresponding output values.

```
fuzout = evalfis(fis,datain);
```

Compute the root mean squared error (RMSE) of the output values of the fuzzy system compared to the expected output values.

```
trnRMSE = norm(fuzout-dataout)/sqrt(length(fuzout))
```

```
trnRMSE = 0.5276
```

Validate the performance of the fuzzy system using the validation data.


```
valfuzout = evalfis(fis,valdatain);
```

```
valRMSE = norm(valfuzout-valdataout)/sqrt(length(valfuzout))
```

```
valRMSE = 0.6179
```

Plot the output of the model against the validation data.

```
figure
plot(valdataout)
hold on
plot(valfuzout,"o")
hold off
ylabel("Output value")
legend("Validation data","FIS output","Location","northwest")
```



The plot shows that the model does not predict the validation data well.

Tune FIS Using ANFIS

To improve the FIS performance, you can optimize the system using the `anfisc` function. First, try using a relatively short training period (20 epochs) without using validation data, and then test the resulting FIS model against the validation data.

```
opt = anfiscOptions('InitialFIS',fis,...
    'EpochNumber',20,...
    'InitialStepSize',0.1);
fis2 = anfisc([datain dataout],opt);
```

ANFIS info:

```
Number of nodes: 44
Number of linear parameters: 18
Number of nonlinear parameters: 30
Total number of parameters: 48
Number of training data pairs: 75
Number of checking data pairs: 0
Number of fuzzy rules: 3
```

Start training ANFIS ...

```
1    0.527607
2    0.513727
3    0.492996
```

```

4      0.499985
5      0.490585
6      0.492924
Step size decreases to 0.090000 after epoch 7.
7      0.48733
8      0.485037
9      0.480813
Step size increases to 0.099000 after epoch 10.
10     0.475097
11     0.469759
12     0.462516
13     0.451177
Step size increases to 0.108900 after epoch 14.
14     0.447856
15     0.444357
16     0.433904
17     0.433739
Step size increases to 0.119790 after epoch 18.
18     0.420408
19     0.420512
20     0.420275

```

Designated epoch number reached. ANFIS training completed at epoch 20.

Minimal training RMSE = 0.420275

Assess the performance of the FIS on both the training data and the validation data.

```

fuzout2 = evalfis(fis2,datain);
trnRMSE2 = norm(fuzout2-dataout)/sqrt(length(fuzout2))

trnRMSE2 = 0.4203

valfuzout2 = evalfis(fis2,valdatain);
valRMSE2 = norm(valfuzout2-valdataout)/sqrt(length(valfuzout2))

valRMSE2 = 0.5894


```

The model performance shows substantial improvement with respect to the training data but only slightly with respect to the validation data. Plot the improved model output against the validation data.

```

figure
plot(valdataout)
hold on
plot(valfuzout, 'o')
plot(valfuzout2, 'x')
hold off
ylabel('Output value')
legend("Validation data",...
      "Initial FIS: RMSE = " + num2str(valRMSE), ...
      "Tuned FIS: RMSE = " + num2str(valRMSE2), ...
      "Location", "northwest")

```



Check ANFIS Result for Overfitting

When tuning a FIS, you can detect overfitting when the validation error starts to increase while the training error continues to decrease.

To check the model for overfitting, use `anfis` with validation data to train the model for 200 epochs. First configure the ANFIS training options by modifying the existing `anfisOptions` option set. Specify the number of epochs and validation data. Since the number of training epochs is larger, suppress the display of training information in the Command Window.

```
opt.EpochNumber = 200;
opt.ValidationData = [valdatain valdataout];
opt.DisplayANFISInformation = 0;
opt.DisplayErrorValues = 0;
opt.DisplayStepSize = 0;
opt.DisplayFinalResults = 0;
```

Train the FIS.

```
[fis3,trnErr,stepSize,fis4,valErr] = anfis([datain dataout],opt);
```

Here:

- `fis3` is the FIS object when the training error reaches a minimum.
- `fis4` is the snapshot FIS object when the validation data error reaches a minimum.
- `stepSize` is a history of the training step sizes.

- `trnErr` is the RMSE using the training data.
- `valErr` is the RMSE using the validation data for each training epoch.

After the training completes, validate the model using the training and validation data.

```
fuzout4 = evalfis(fis4,datain);
trnRMSE4 = norm(fuzout4-dataout)/sqrt(length(fuzout4))

trnRMSE4 = 0.3405


valfuzout4 = evalfis(fis4,valdatain);
valRMSE4 = norm(valfuzout4-valdataout)/sqrt(length(valfuzout4))

valRMSE4 = 0.5821
```

The error with the training data is the lowest thus far, and the error with the validation data is also slightly lower than before. This result suggests possible overfitting, which occurs when you fit the fuzzy system to the training data so well that it no longer does a good job of fitting the validation data. The result is a loss of generality.


View the improved model output. Plot the model output against the validation data.

```
figure
plot(valdataout)
hold on
plot(valfuzout2,'o')
plot(valfuzout4,'x')
hold off
ylabel('Output value')
legend("Validation data",...
    "Tuned FIS: RMSE = " + num2str(valRMSE2), ...
    "Min val. error FIS: RMSE = " + num2str(valRMSE4), ...
    "Location","northwest")
```



Next, plot the training error `trnErr`.


```
figure
plot(trnErr)
title('Training Error')
xlabel('Number of Epochs')
ylabel('Error')
```



This plot shows that the training error settles at about the 60th epoch.

Plot the validation error `valErr`.

```
figure
plot(valErr)
title('Validation Error')
xlabel('Number of Epochs')
ylabel('Error')
```



The plot shows that the smallest value of the validation data error occurs at epoch 52. After this point, it increases slightly even as `anfis` continues to minimize the error against the training data. This pattern is a sign of overfitting. Depending on the specified error tolerance, plotting the validation error can also indicate the ability of the model to generalize the test data.

See Also

`subclust` | `anfis`

More About


- “Fuzzy Clustering” on page 4-2

Cluster Data Using Clustering Tool

Using the Clustering tool, you can cluster data using fuzzy c-means or subtractive clustering. For more information on the clustering methods, see “Fuzzy Clustering” on page 4-2.

To open the tool, at the MATLAB command line, type:

```
findcluster
```



Use the Clustering tool to perform the following tasks:

- 1 Load and plot the data.
- 2 Perform the clustering.
- 3 Save the cluster center.

Access the online help topics by clicking **Info** or using the **Help** menu.

Load and Plot Data

To load a data set, perform either of the following actions:

- Click **Load Data**, and select the file containing the data.
- Open the Clustering Tool with a data set directly by calling `findcluster` with the data set as an input argument.

For example, enter:

```
findcluster('clusterdemo.dat')
```

The data set file must have the extension `.dat`. Each line of the data set file contains one data point. For example, if you have 5-dimensional data with 100 data points, the file contains 100 lines, and each line contains five values.


The Clustering tool works on multidimensional data sets, but displays only two of those dimensions on the plot. To select other dimensions in the data set for plotting, you can use the drop-down lists under **X-axis** and **Y-axis**.

Cluster Data

To start clustering the data:

- 1 Choose the clustering function `fcm` (fuzzy C-Means clustering) or `subtractiv` (subtractive clustering) from the drop-down menu under **Methods**.
- 2 Set options for:
 - Fuzzy c-means clustering using the **Cluster Num**, **Max Iteration**, **Min**, and **Exponent** fields. For information on these options, see `fcm`.
 - Subtractive clustering using the **Influence Range**, **Squash**, **Aspect Ratio**, and **Reject Ratio** fields. To use a different influence range for each data column, specify **Influence Range** as a vector with the number of elements equal to the number of columns. For information on these options, see `subclust`.
- 3 Cluster the data by clicking **Start**.

Once the clustering is complete, the cluster centers appear in black.



Tip Using the Clustering tool, you can obtain only the computed cluster centers. To obtain additional information for:

- Fuzzy c-means clustering, such as the fuzzy partition matrix, cluster the data using `fcm`.
- Subtractive clustering, such as the range of influence in each data dimension, cluster the data using `subclust`.

To use the same clustering data with either `fcm` or `subclust`, first load the data file into the MATLAB workspace. For example, at the MATLAB command line, type:

```
load clusterdemo.dat
```

Save Cluster Centers

To save the cluster centers, click **Save Center**.

See Also

`findcluster` | `fcm` | `subclust`

More About

- “Fuzzy Clustering” on page 4-2

Fuzzy Logic in Simulink

- “Simulate Fuzzy Inference Systems in Simulink” on page 5-2
- “Water Level Control in a Tank” on page 5-11
- “Temperature Control in a Shower” on page 5-17
- “Implement Fuzzy PID Controller in Simulink Using Lookup Table” on page 5-24

Simulate Fuzzy Inference Systems in Simulink

You can simulate a fuzzy inference system (FIS) in Simulink using either the Fuzzy Logic Controller or Fuzzy Logic Controller with Ruleviewer blocks. Alternatively, you can evaluate fuzzy systems at the command line using `evalfis`.

Using the Fuzzy Logic Controller, you can simulate traditional type-1 fuzzy inference systems (`mamfis` and `sugfis`) and type-2 fuzzy inference systems (`mamfistype2` and `sugfistype2`). The Fuzzy Logic Controller with Ruleviewer block supports only type-1 systems.

For more information on creating fuzzy inference systems, see “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14 and “Build Fuzzy Systems at the Command Line” on page 2-31.


Simulate Fuzzy Inference System

Once you have implemented a fuzzy inference system using **Fuzzy Logic Designer**, using **Neuro-Fuzzy Designer**, or at the command line, you can simulate the system in Simulink.

For this example, you control the level of water in a tank using a fuzzy inference system implemented using a Fuzzy Logic Controller block. Open the `sltank` model.

```
open_system('sltank')
```

Water Level Control in a Tank
Copyright 2002-2018 The MathWorks, Inc.



For this system, you control the water that flows into the tank using a valve. The outflow rate depends on the diameter of the output pipe, which is constant, and the pressure in the tank, which varies with water level. Therefore, the system has nonlinear characteristics.

The two inputs to the fuzzy system are the water level error, `level`, and the rate of change of the water level, `rate`. The output of the fuzzy system is the rate at which the control valve is opening or closing, `valve`.

To implement a fuzzy inference system, specify the **FIS name** parameter of the Fuzzy Logic Controller block as the name of a FIS object in the MATLAB® workspace. In this example, the block uses the `mamfis` object `tank`.

For more information on this system, see “Water Level Control in a Tank” on page 5-11.

As a first attempt to control the water level, set the following rules in the FIS. These rules adjust the valve based on only the water level error.



- If the water level is okay, then do not adjust the valve.
- If the water level is low, then open the valve quickly.
- If the water level is high, then close the valve quickly.

Specify the rules by creating a vector of `fisrule` objects and assigning it to the `Rules` property of the `tank` FIS object.

```
rule1 = "If level is okay then valve is no_change";  
rule2 = "If level is low then valve is open_fast";  
rule3 = "If level is high then valve is close_fast";  
rules = [rule1 rule2 rule3];  
tank.Rules = fisrule(rules);
```

Simulate the model, and view the water level.

```
open_system('sltank/Comparison')  
sim('sltank',100)
```



Water Level Control



These rules are insufficient for controlling the system, since the water level oscillates around the setpoint.

To reduce the oscillations, add two more rules to the system. These rules adjust the valve based on the rate of change of the water level when the water level is near the setpoint.


- If the water level is okay and increasing, then close the valve slowly.
- If the water level is okay and decreasing, then open the valve slowly.


To add these rules, use the `addRule` function.

```
rule4 = "If level is okay and rate is positive then valve is close_slow";  
rule5 = "If level is okay and rate is negative then valve is open_slow";  
newRules = [rule4 rule5];  
tank = addRule(tank,newRules);
```

Simulate the model.

```
sim('sltank',100)
```






The water level now tracks the setpoint without oscillating.

You can also simulate fuzzy systems using the Fuzzy Logic Controller with Ruleviewer block. The `sltankrule` model is the same as the `sltank` model, except that it uses the Fuzzy Logic Controller with Ruleviewer block.


```
open_system('sltankrule')
```


Water Level Control in a Tank
Copyright 2002-2018 The MathWorks, Inc.



During simulation, this block displays the Rule Viewer from the **Fuzzy Logic Designer** app.

```
sim('sltankrule',100)
```





If you pause the simulation, you can examine the FIS behavior by manually adjusting the input variable values in the Rule Viewer, and observing the inference process and output.

You can also access the **Fuzzy Logic Designer** editors from the Rule Viewer. From the Rule Viewer, you can then adjust the parameters of your fuzzy system using these editors, and export the updated system to the MATLAB workspace. To simulate the updated FIS, restart the simulation. For more information on using these editors, see “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14.

Access Intermediate Fuzzy Inference Results

You can access intermediate fuzzy inference results using the Fuzzy Logic Controller block. You can use this data to visualize the fuzzy inference process or troubleshoot the performance of your FIS. To access this data, enable the corresponding parameters in the block, and connect signals to the corresponding output ports.

Block Parameter	Description	Output Port
Fuzzified Inputs	Fuzzified input values, obtained by evaluating the input membership functions of each rule at the current input values.	fi
Rule firing strengths	Rule firing strengths, obtained by evaluating the antecedent of each rule.	rf _s
Rule outputs	Rule outputs, obtained by evaluating the consequent of each rule.	ro
Aggregated outputs	Aggregate output for each output variable, obtained by combining the corresponding outputs from all the rules.	ao

For more information, see Fuzzy Logic Controller.

Simulation Modes

The Fuzzy Logic Controller block has the following two simulation modes:

- **Interpreted execution** — Simulate fuzzy systems using precompiled MEX files. Using this option reduces the initial compilation time of the model.
- **Code generation** — Simulate fuzzy system without precompiled MEX files. Use this option when simulating fuzzy systems for code generation applications. Doing so simulates your system using the same code path used for generated code.

To select a simulation mode, set the **Simulate using** parameter of the block. By default, the block uses **Interpreted execution** mode for simulation.

Map Command-Line Functionality to Fuzzy Logic Controller Block

The parameters and ports of the Fuzzy Logic Controller block map to the input and output arguments of `evalfis` or the properties of `evalfisOptions`. The following table shows the block parameters and ports that map to `evalfis` arguments.

evalfis Argument	Description	Block Parameter or Port
<code>fis</code>	Fuzzy inference system	FIS name
<code>input</code> , when a single row	Input variable values	<code>in</code>
<code>output</code> , when a single row	Output variable values	<code>out</code>
<code>fuzzifiedIn</code>	Fuzzified inputs	<code>fi</code>
<code>ruleOut</code>	Rule outputs	<code>ro</code>
<code>aggregateOut</code>	Aggregated outputs	<code>ao</code>
<code>ruleFiring</code>	Rule firing strengths	<code>rfs</code>

The following table shows the block parameters that map to `evalfisOptions` properties.

evalfisOptions Property	Description	Block Parameter or Port
<code>NumSamplePoints</code>	Number of points in output fuzzy sets	Number of samples for output discretization
<code>OutOfRangeInputValueMessage</code>	Diagnostic message behavior when an input is out of range	Out of range input value
<code>NoRuleFiredMessage</code>	Diagnostic message behavior when no rules fire	No rule fired
<code>EmptyOutputFuzzySetMessage</code>	Diagnostic message behavior when an output fuzzy set is empty	Empty output fuzzy set

The remaining parameters of the Fuzzy Logic Controller block do not map to arguments of `evalfis`. Also, unlike the Fuzzy Logic Controller block, `evalfis` does not support fixed-point data for simulation or code generation.

See Also

Blocks

Fuzzy Logic Controller | Fuzzy Logic Controller with Ruleviewer

More About

- “Temperature Control in a Shower” on page 5-17
- “Water Level Control in a Tank” on page 5-11


Water Level Control in a Tank

This model shows how to implement a fuzzy inference system (FIS) in a Simulink® model.

Simulink Model

This model controls the level of water in a tank using a fuzzy inference system implemented using a Fuzzy Logic Controller block. Open the `sltank` model.

```
open_system('sltank')
```




For this system, you control the water that flows into the tank using a valve. The outflow rate depends on the diameter of the output pipe, which is constant, and the pressure in the tank, which varies with water level. Therefore, the system has nonlinear characteristics.


Fuzzy Inference System

The fuzzy system is defined in a FIS object, `tank`, in the MATLAB® workspace. For more information on how to specify a FIS in a Fuzzy Logic Controller, see Fuzzy Logic Controller.

The two inputs to the fuzzy system are the water level error, `level`, and the rate of change of the water level, `rate`. Each input has three membership functions.


```
figure
plotmf(tank,'input',1)
figure
plotmf(tank,'input',2)
```





The output of the fuzzy system is the rate at which the control valve is opening or closing, valve, which has five membership functions.

```
plotmf(tank, 'output', 1)
```



Due to the diameter of the outflow pipe, the water tank in this system empties more slowly than it fills up. To compensate for this imbalance, the `close_slow` and `open_slow` valve membership functions are not symmetrical. A PID controller does not support such asymmetry.

The fuzzy system has five rules. The first three rules adjust the valve based on only the water level error.

- If the water level is okay, then do not adjust the valve.
- If the water level is low, then open the valve quickly.
- If the water level is high, then close the valve quickly.

The other two rules adjust the valve based on the rate of change of the water level when the water level is near the setpoint.

- If the water level is okay and increasing, then close the valve slowly.
- If the water level is okay and decreasing, then open the valve slowly.

tank.Rules

ans =

1x5 fisrule array with properties:

Description
Antecedent

Consequent
Weight
Connection

Details:

Description


	Description
1	"level==okay => valve=no_change (1)"
2	"level==low => valve=open_fast (1)"
3	"level==high => valve=close_fast (1)"
4	"level==okay & rate==positive => valve=close_slow (1)"
5	"level==okay & rate==negative => valve=open_slow (1)"


In this model, you can also control the water level using a PID controller. To switch to the PID controller, set the const block to a value greater than or equal to zero.

Simulation

The model simulates the controller with periodic changes in the setpoint of the water level. Run the simulation.

```
sim('sltank',100)
open_system('sltank/Comparison')
```





The water level tracks the setpoint well. You can adjust the performance of the controller by modifying the rules of the tank FIS. For example, if you remove the last two rules, which are analogous to a derivative control action, the controller performs poorly, with large oscillations in the water level.

See Also

Blocks

Fuzzy Logic Controller | Fuzzy Logic Controller with Ruleviewer

More About

- “Simulate Fuzzy Inference Systems in Simulink” on page 5-2
- “Temperature Control in a Shower” on page 5-17

Temperature Control in a Shower


This model shows how to implement a fuzzy inference system (FIS) in a Simulink® model.

Simulink Model

The model controls the temperature of a shower using a fuzzy inference system implemented using a Fuzzy Logic Controller block. Open the shower model.

```
open_system('shower')
```

Temperature Control in a Shower
Copyright (c) 2002-2018 The MathWorks, Inc.



For this system, you control the flow rate and temperature of a shower by adjusting hot and cold water valves.


Since there are two inputs for the fuzzy system, the model concatenates the input signals using a Mux block. The output of the Mux block is connected to the input of the Fuzzy Logic Controller block. Similarly, the two output signals are obtained using a Demux block connected to the controller.


Fuzzy Inference System

The fuzzy system is defined in a FIS object, `fis`, which is loaded in the MATLAB® workspace when the model opens. For more information on how to specify a FIS in a Fuzzy Logic Controller block, see Fuzzy Logic Controller.

The two inputs to the fuzzy system are the temperature error, `temp`, and the flow rate error, `flow`. Each input has three membership functions.


```
figure
plotmf(fis,'input',1)
figure
plotmf(fis,'input',2)
```






The two outputs of the fuzzy system are the rate at which the cold and hot water valves are opening or closing, cold and hot respectively. Each output has five membership functions.

```
figure
plotmf(fis, 'output', 1)
figure
plotmf(fis, 'output', 2)
```





The fuzzy system has nine rules for adjusting the hot and cold water valves based on the flow and temperature errors. The rules adjust the total flow rate based on the flow error, and adjust the relative hot and cold flow rates based on the temperature error.

```
fis.Rules
```

```
ans =
```

```
1x9 fisrule array with properties:
```

```
Description
Antecedent
Consequent
Weight
Connection
```

```
Details:
```

```
Description
```

```
1 "temp==cold & flow==soft => cold=openSlow, hot=openFast (1)"
2 "temp==cold & flow==good => cold=closeSlow, hot=openSlow (1)"
3 "temp==cold & flow==hard => cold=closeFast, hot=closeSlow (1)"
4 "temp==good & flow==soft => cold=openSlow, hot=openSlow (1)"
5 "temp==good & flow==good => cold=steady, hot=steady (1)"
6 "temp==good & flow==hard => cold=closeSlow, hot=closeSlow (1)"
7 "temp==hot & flow==soft => cold=openFast, hot=openSlow (1)"
```

```

8 "temp==hot & flow==good => cold=openSlow, hot=closeSlow (1)"
9 "temp==hot & flow==hard => cold=closeSlow, hot=closeFast (1)"

```



Simulation

The model simulates the controller with periodic changes in the setpoints of the water temperature and flow rate.

```

set_param('shower/flow scope','Open','on','Ymin','0','Ymax','1')
set_param('shower/temp scope','Open','on','Ymin','15','Ymax','30')
sim('shower',50)

```



The flow rate tracks the setpoint well. The temperature also tracks its setpoint, though there are temperature deviations when the controller adjusts to meet a new flow setpoint.

```
bdclose('shower') % Closing model also clears its workspace variables.
```

See Also

Blocks

Fuzzy Logic Controller

More About


- “Simulate Fuzzy Inference Systems in Simulink” on page 5-2
- “Water Level Control in a Tank” on page 5-11

Implement Fuzzy PID Controller in Simulink Using Lookup Table

This example shows how to implement a fuzzy inference system for nonlinear PID control using a 2-D Lookup Table block.

Overview

A fuzzy inference system (FIS) maps given inputs to outputs using fuzzy logic. For example, a typical mapping of a two-input, one-output fuzzy controller can be depicted in a 3-D plot. The plot is often referred to as a *control surface* plot.



For control applications, typical FIS inputs are the error ($e(k)$) and change of error ($e(k) - e(k-1)$), E and CE respectively in the control surface plot. The FIS output is the control action inferred from the fuzzy rules, u in the surface plot. Fuzzy Logic Toolbox™ provides commands and apps for designing a FIS for a desired control surface. You can then simulate the designed FIS using the Fuzzy Logic Controller block in Simulink®.

You can often approximate nonlinear control surfaces using lookup tables to simplify the generated code and improve execution speed. For example, you can replace a Fuzzy Logic Controller block in Simulink with a set of Lookup Table blocks, one table for each output defined in the FIS. You can compute the data used in the lookup table using the `evalfis` command.

For this example, you design a nonlinear fuzzy PID controller for a plant in Simulink. The plant is a single-input, single-output system in discrete time. The design goal is to achieve good reference tracking performance.

```
Ts = 0.1;
Plant = c2d(zpk([], [-1 -3 -5], 1), Ts);
```

You also implement the fuzzy inference system using a 2-D lookup table that approximates the control surface and achieves the same control performance.


Fuzzy PID Controller Structure

The fuzzy controller in this example is in the feedback loop and computes PID-like actions using fuzzy inference. Open the Simulink model.

```
open_system('sllookuptable')
```


Using Lookup Table to Implement a Fuzzy PID Controller

Copyright (c) 2002-2018 The MathWorks, Inc.



The fuzzy PID controller uses a parallel structure as shown in the Fuzzy PID subsystem. For more information, see [1]. The controller is a combination of fuzzy PI control and fuzzy PD control.

```
open_system('sllookuptable/Fuzzy PID')
```




The fuzzy PID controller uses the change of the output $-(y(k) - y(k-1))$, instead of change of error $e(k) - e(k-1)$, as the second input signal to the FIS. Doing so prevents the step change in reference signal from directly triggering the derivative action. The two gain blocks, GCE and GCU, in the feed forward path from r to u , ensure that the error signal e is used in proportional action when the fuzzy PID controller is linear.

Design Conventional PID Controller

The conventional PID controller in this example is a discrete-time PID controller with Backward Euler numerical integration in both the integral and derivative actions. The controller gains are K_p , K_i , and K_d .

```
open_system('slookupable/Conventional PID')
```



Similar to the fuzzy PID controller, the input signal to the derivative action is $-y(k)$, instead of $e(k)$.

You can tune the PID controller gains manually or using tuning formulas. In this example, obtain the initial PID design using the `pidtune` command from Control System Toolbox™.

Define the PID structure, tune the controller, and extract the PID gains.

```
C0 = pid(1,1,1, 'Ts', Ts, 'IF', 'B', 'DF', 'B');
C = pidtune(Plant, C0)
[Kp, Ki, Kd] = piddata(C);
```

C =

$$K_p + K_i * \frac{T_s * z}{z - 1} + K_d * \frac{z - 1}{T_s * z}$$

with $K_p = 30.6$, $K_i = 25.2$, $K_d = 9.02$, $T_s = 0.1$

Sample time: 0.1 seconds
Discrete-time PID controller in parallel form.

Design Equivalent Linear Fuzzy PID Controller

By configuring the FIS and selecting the four scaling factors, you can obtain a linear fuzzy PID controller that reproduces the control performance of the conventional PID controller.

First, configure the fuzzy inference system so that it produces a linear control surface from inputs E and CE to output u. The FIS settings are based on design choices described in [2]:

- Use a Sugeno style fuzzy inference system with default inference methods.
- Normalize the ranges of both inputs to [-10 10].
- Use triangular input membership functions that overlap their neighbor functions at a membership value of 0.5.
- Use an output range of [-20 20].
- Use constant output membership functions.

Construct the fuzzy inference system.

```
FIS = sugfis;
```

Define input variable E.

```
FIS = addInput(FIS, [-10 10], 'Name', 'E');
FIS = addMF(FIS, 'E', 'trimf', [-20 -10 0], 'Name', 'Negative');
FIS = addMF(FIS, 'E', 'trimf', [-10 0 10], 'Name', 'Zero');
FIS = addMF(FIS, 'E', 'trimf', [0 10 20], 'Name', 'Positive');
```

Define input CE.

```
FIS = addInput(FIS, [-10 10], 'Name', 'CE');
FIS = addMF(FIS, 'CE', 'trimf', [-20 -10 0], 'Name', 'Negative');
FIS = addMF(FIS, 'CE', 'trimf', [-10 0 10], 'Name', 'Zero');
FIS = addMF(FIS, 'CE', 'trimf', [0 10 20], 'Name', 'Positive');
```

Define output variable u with constant membership functions.

```
FIS = addOutput(FIS, [-20 20], 'Name', 'u');
FIS = addMF(FIS, 'u', 'constant', -20, 'Name', 'LargeNegative');
FIS = addMF(FIS, 'u', 'constant', -10, 'Name', 'SmallNegative');
FIS = addMF(FIS, 'u', 'constant', 0, 'Name', 'Zero');
FIS = addMF(FIS, 'u', 'constant', 10, 'Name', 'SmallPositive');
FIS = addMF(FIS, 'u', 'constant', 20, 'Name', 'LargePositive');
```

Define the following fuzzy rules:

- 1 If E is Negative and CE is Negative, then u is LargeNegative.
- 2 If E is Negative and CE is Zero, then u is SmallNegative.
- 3 If E is Negative and CE is Positive, then u is Zero.
- 4 If E is Zero and CE is Negative, then u is SmallNegative.
- 5 If E is Zero and CE is Zero, then u is Zero.


- 6 If E is Zero and CE is Positive, then u is SmallPositive.
- 7 If E is Positive and CE is Negative, then u is Zero.
- 8 If E is Positive and CE is Zero, then u is SmallPositive.
- 9 If E is Positive and CE is Positive, then u is LargePositive.

```
ruleList = [1 1 1 1 1; % Rule 1
            1 2 2 1 1; % Rule 2
            1 3 3 1 1; % Rule 3
            2 1 2 1 1; % Rule 4
            2 2 3 1 1; % Rule 5
            2 3 4 1 1; % Rule 6
            3 1 3 1 1; % Rule 7
            3 2 4 1 1; % Rule 8
            3 3 5 1 1]; % Rule 9
FIS = addRule(FIS,ruleList);
```

While you implement your FIS from the command line in this example, you can alternatively build your FIS using the **Fuzzy Logic Designer** app.

Plot the linear control surface.

```
gensurf(FIS)
```



Determine scaling factors G_E , G_{CE} , G_{CU} , and G_U from the K_p , K_i , and K_d gains of by the conventional PID controller. Comparing the expressions of the traditional PID and the linear fuzzy PID, the variables are related as follows:

- $K_p = G_{CU} * G_{CE} + G_U * G_E$
- $K_i = G_{CU} * G_E$
- $K_d = G_U * G_{CE}$

Assume that the maximum reference step is 1, and thus the maximum error e is 1. Since the input range of E is $[-10 \ 10]$, set G_E to 10. You can then solve for G_{CE} , G_{CU} , and G_U .

```
GE = 10;
GCE = GE*(Kp-sqrt(Kp^2-4*Ki*Kd))/2/Ki;
GCU = Ki/GE;
GU = Kd/GCE;
```

Implement Fuzzy Inference System Using 2-D Lookup Table


The fuzzy controller block has two inputs (E and CE) and one output (u). Therefore, you can replace the fuzzy system using a 2-D lookup table.

To generate a 2-D lookup table from your FIS, loop through the input universe, and compute the corresponding output values using `evalfis`. Since the control surface is linear, you can use a few sample points for each input variable.

```
Step = 10;
E = -10:Step:10;
CE = -10:Step:10;
N = length(E);
LookUpTableData = zeros(N);
for i=1:N
    for j=1:N
        % Compute output u for each combination of sample points.
        LookUpTableData(i,j) = evalfis(FIS,[E(i) CE(j)]);
    end
end
```

View the fuzzy PID controller using 2-D lookup table.

```
open_system('sllookuptable/Fuzzy PID using Lookup Table')
```



The only difference compared to the Fuzzy PID controller is that the Fuzzy Logic Controller block is replaced with a 2-D Lookup Table block.


When the control surface is linear, a fuzzy PID controller using the 2-D lookup table produces the same result as one using the Fuzzy Logic Controller block.

Simulate Closed-Loop Response in Simulink

The Simulink model simulates three different controller subsystems, namely Conventional PID, Fuzzy PID, and Fuzzy PID using Lookup Table, to control the same plant.

Run the simulation. To compare the closed-loop responses to a step reference change, open the scope. As expected, all three controllers produce the same result.

```
sim('sllookuptable')
open_system('sllookuptable/Scope')
```



Design Fuzzy PID Controller with Nonlinear Control Surface

Once you have a linear fuzzy PID controller, you can obtain a nonlinear control surface by adjusting your FIS settings, such as its style, membership functions, and rule base.

For this example, design a steep control surface using a Sugeno-type FIS. Each input set has two terms (Positive and Negative), and the number of rules is reduced to four.

Construct the FIS.

```
FIS = sugfis;
```

Define input E.

```
FIS = addInput(FIS, [-10 10], 'Name', 'E');
FIS = addMF(FIS, 'E', 'gaussmf', [7 -10], 'Name', 'Negative');
FIS = addMF(FIS, 'E', 'gaussmf', [7 10], 'Name', 'Positive');
```

Define input CE.

```
FIS = addInput(FIS, [-10 10], 'Name', 'CE');
FIS = addMF(FIS, 'CE', 'gaussmf', [7 -10], 'Name', 'Negative');
FIS = addMF(FIS, 'CE', 'gaussmf', [7 10], 'Name', 'Positive');
```

Define output u.

```
FIS = addOutput(FIS,[-20 20], 'Name','u');
FIS = addMF(FIS,'u','constant',-20,'Name','Min');
FIS = addMF(FIS,'u','constant',0,'Name','Zero');
FIS = addMF(FIS,'u','constant',20,'Name','Max');
```


Define the following rules:

- 1 If E is Negative and CE is Negative, then u is Min.
- 2 If E is Negative and CE is Positive, then u is Zero.
- 3 If E is Positive and CE is Negative, then u is Zero.
- 4 If E is Positive and CE is Positive, then u is Max.

```
ruleList = [1 1 1 1;... % Rule 1
            1 2 2 1;... % Rule 2
            2 1 2 1;... % Rule 3
            2 2 3 1]; % Rule 4
FIS = addRule(FIS,ruleList);
```

View the 3-D nonlinear control surface. This surface has a higher gain near the center of the E and CE plane than the linear surface has, which helps reduce the error more quickly when the error is small. When the error is large, the controller becomes less aggressive to avoid possible saturation.

gensurf(FIS)




Before starting the simulation, update the lookup table with the new control surface data. Since the surface is nonlinear, to obtain a sufficient approximation, add more sample points.

```
Step = 1;
E = -10:Step:10;
CE = -10:Step:10;
N = length(E);
LookupTableData = zeros(N);
for i=1:N
    for j=1:N
        % Compute output u for each combination of sample points.
        LookupTableData(i,j) = evalfis(FIS,[E(i) CE(j)]);
    end
end
end
```

Run the simulation.

```
sim('sllookuptable')
```



Compared with the traditional linear PID controller (the response curve with large overshoot), the nonlinear fuzzy PID controller reduces the overshoot by 50%. The two response curves from the nonlinear fuzzy controllers almost overlap, which indicates that the 2-D lookup table approximates the fuzzy system well.

```
bdclose('sllookuptable') % Closing model also clears its workspace variables.
```

Conclusion

You can approximate a nonlinear fuzzy PID controller using a lookup table. By replacing a Fuzzy Logic Controller block with Lookup Table blocks in Simulink, you can deploy a fuzzy controller with simplified generated code and improved execution speed.

References

[1] Xu, J. X., Hang, C. C., Liu, C. "Parallel structure and tuning of a fuzzy PID controller." *Automatica*, Vol. 36, pp. 673-684. 2000.

[2] Jantzen, J. *Tuning of Fuzzy PID Controllers*, Technical Report, Dept. of Automation, Technical University of Denmark. 1999.

See Also

Blocks

Fuzzy Logic Controller | 2-D Lookup Table

More About

- "Simulate Fuzzy Inference Systems in Simulink" on page 5-2

Deployment

- “Deploy Fuzzy Inference Systems” on page 6-2
- “Generate Code for Fuzzy System Using Simulink Coder” on page 6-3
- “Generate Structured Text for Fuzzy System Using Simulink PLC Coder” on page 6-7
- “Generate Code for Fuzzy System Using MATLAB Coder” on page 6-10

Deploy Fuzzy Inference Systems

You can deploy a fuzzy inference system (FIS) by generating code in either Simulink or MATLAB. You can generate code for both type-1 (mamfis, sugfis) and type-2 fuzzy (mamfistype2, sugfistype2) inference systems. All fuzzy inference system options, including custom inference functions, support code generation.

Generate Code in Simulink

You can generate code for evaluating fuzzy inference systems in Simulink using the Fuzzy Logic Controller block. You can generate code for double-precision, single-precision, or fixed-point data using Simulink Coder™ or Simulink PLC Coder™.

For more information, see “Generate Code for Fuzzy System Using Simulink Coder” on page 6-3 and “Generate Structured Text for Fuzzy System Using Simulink PLC Coder” on page 6-7.

Generate Code in MATLAB

You can generate code for evaluating fuzzy inference systems in MATLAB. You can generate code for double-precision or single-precision data using MATLAB Coder.

Code generation in MATLAB does not support fuzzy inference system objects. Instead, convert your fuzzy system into a homogeneous structure using `getFISCodeGenerationData`, and pass the resulting structure to `evalfis`.

For more information, see “Generate Code for Fuzzy System Using MATLAB Coder” on page 6-10.

Note Code generation does not support the construction of fuzzy systems at the command line.

See Also

Functions

`mamfis` | `sugfis` | `evalfis`

Blocks

Fuzzy Logic Controller

More About

- “Build Fuzzy Systems at the Command Line” on page 2-31
- “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14

Generate Code for Fuzzy System Using Simulink Coder


You can generate code for a Fuzzy Logic Controller block using Simulink® Coder™. For more information on generating code, see “Generate Code Using Simulink Coder” (Simulink Coder).

While this example generates code for a type-1 Sugeno fuzzy inference system, the workflow also applies to Mamdani and type-2 fuzzy systems.

Generate Code for Fuzzy Inference System

By default, the Fuzzy Logic Controller block uses double-precision data for simulation and code generation. The fuzzyPID model is configured to use double-precision data. For more information on configuring your fuzzy inference system for code generation, see Fuzzy Logic Controller.

```
mdl = 'fuzzyPID';
open_system(mdl)
```



It is good practice to validate the performance of the system in Simulink. Run the simulation. The model saves the output response u to the MATLAB® workspace.

```
sim(mdl)
```

To generate code for the model, use the `slbuild` (Simulink) function. For this example, suppress the Command Window output for the build process.

```
set_param(mdl, 'RTWVerbose', 'off')
slbuild(mdl)
```

```
### Starting build procedure for: fuzzyPID
### Successful completion of build procedure for: fuzzyPID
```

Build Summary

Top model targets built:

Model	Action	Rebuild Reason
fuzzyPID	Code generated and compiled	Code generation information file does not exist.

1 of 1 models built (0 models already up to date)

Build duration: 0h 0m 33.537s

By default, Simulink Coder generates C code for a generic real-time target. To select a different target file and language, in the Configuration Parameters dialog box, modify the **System target file** and **Language** parameters, respectively.

The generated code is stored in a new `fuzzyPID_grt_rtw` folder in your current working folder. The name of this folder depends on the selected target file.

On a Windows® system, by default, an executable file named `fuzzyPID.exe` is also added to the current working folder. To generate code without compilation, in the Configuration parameters dialog box, select the **Generate code only** parameter before generating code.

Run the executable.

```
if ispc
    status = system(mdl);
else
    disp('The example only runs the executable on Windows system.');
```


end

```
** starting the model **
** created fuzzyPID.mat **
```

After the executable completes successfully (`status = 0`), the software creates a `fuzzyPID.mat` data file that contains the simulation results.

You can compare the output response from the generated code, `rtw_y`, with the output from the Simulink simulation, `y`, using the following code.

```
load fuzzyPID.mat
plot(tout,y,'b-',rt_tout,rt_y,'ro')
legend('Simulink','Executable','Location','Southeast')
```



The result from the generated code matches the Simulink simulation.

You can also generate code for just the controller subsystem in this model. To do so, specify the subsystem when calling the `slbuild` function.

```
slbuild([mdl '/Fuzzy PID'])

### Starting build procedure for: Fuzzy0
### Successful completion of build procedure for: Fuzzy0
```

Build Summary

Top model targets built:

Model	Action	Rebuild Reason
Fuzzy0	Code generated and compiled	Code generation information file does not exist.

1 of 1 models built (0 models already up to date)
Build duration: 0h 0m 16.461s

You can deploy generated code according to your application needs. For example, you can configure the properties of executable files and create static or dynamic libraries. For more information, see “Build Process Workflow for Real-Time Systems” (Simulink Coder).

Generate Code for Other Data Types


The Fuzzy Logic Controller block also supports single-precision and fixed-point data for simulation and code generation. In both cases, your resulting fuzzy system has decreased accuracy compared to an equivalent double-precision fuzzy system. Use:

- Single-precision data to reduce the memory footprint of your system.
- Fixed-point data if your target platform only supports fixed-point arithmetic.

To use one of these data types, set the **Data type** property of the block, and configure the other components in the model to use the same data type.

The `fuzzyPID_single` model is configured for single-precision data. Open the model.

```
mdl2 = 'fuzzyPID_single';
open_system mdl2)
```



In this model, the **Data type** parameter of the Fuzzy Logic Controller block is set to `single`. The Fuzzy Logic Controller block automatically converts input signals to the specified data type. Also, the

Simulate using parameter is set to Code Generation. The **Simulate using** option does not affect the code generation process. Instead, setting this option simulates your fuzzy system using the same code path used by the generated code.

Generate code for this model.

```
set_param mdl2, 'RTWVerbose', 'off')
slbuild(mdl2)

### Starting build procedure for: fuzzyPID_single
### Successful completion of build procedure for: fuzzyPID_single
```

Build Summary

Top model targets built:

Model	Action	Rebuild Reason
fuzzyPID_single	Code generated and compiled	Code generation information file does not exist.

1 of 1 models built (0 models already up to date)
Build duration: 0h 0m 23.287s

Setting the **Data type** parameter of a Fuzzy Logic Controller block ensures that all the inference steps use the specified data type. However, depending on the configuration of other blocks in the model, some of the generated code can still use double-precision data.

See Also

Fuzzy Logic Controller

More About

- “Deploy Fuzzy Inference Systems” on page 6-2
- “Generate Structured Text for Fuzzy System Using Simulink PLC Coder” on page 6-7
- “Generate Code for Fuzzy System Using MATLAB Coder” on page 6-10


Generate Structured Text for Fuzzy System Using Simulink PLC Coder

You can generate Structured Text for a Fuzzy Logic Controller block using Simulink® PLC Coder™. For more information on generating Structured Text, see “Code Generation” (Simulink PLC Coder).

While this example generates Structured Text for a type-1 Sugeno fuzzy inference system, the workflow also applies to Mamdani and type-2 fuzzy systems.


By default, the Fuzzy Logic Controller block uses double-precision data for simulation and code generation. The `fuzzyPID` model is configured to use double-precision data. You can also use either single-precision or fixed-point data. For more information on configuring your fuzzy inference system for code generation, see Fuzzy Logic Controller.

```
mdl = 'fuzzyPID';
open_system(mdl)
```



It is good practice to validate the performance of the system in Simulink before generating code. Run the simulation.

```
sim(mdl)
open_system(['mdl' '/Output'])
```



Close output plot.

```
close_system([mdl '/Output'])
```

To generate Structured Text for the model, use the `plcgeneratecode` (Simulink PLC Coder) function, which generates code for an *atomic subsystem* in a model. To generate code for the Fuzzy PID controller, configure the subsystem as an atomic subsystem by selecting the **Treat as atomic unit** parameter for the subsystem.

```
subsys = [mdl '/Fuzzy PID'];
set_param(subsys, 'TreatAsAtomicUnit', 'on')
```

When generating code for just a Fuzzy Logic Controller block, place the block inside a subsystem, and set the **Treat as atomic unit** parameter of that subsystem.

To generate Structured Text for the Fuzzy PID subsystem, uncomment this line.

```
plcgeneratecode(subsys);

### Generating PLC code for 'fuzzyPID/Fuzzy PID'.
### Using model settings from 'fuzzyPID' for PLC code generation parameters.
### Begin code generation for IDE codesys23.
### Emit PLC code to file.
### Creating PLC code generation report fuzzyPID_codegen_rpt.html.
### PLC code generation successful for 'fuzzyPID/Fuzzy PID'.
### Generated files:
plcsrc\fuzzyPID.exp
```

By default, the software saves the generated code in the following location.

```
plcsrc/fuzzy_PID.exp
```

See Also

Fuzzy Logic Controller

More About

- “Deploy Fuzzy Inference Systems” on page 6-2
- “Generate Code for Fuzzy System Using Simulink Coder” on page 6-3

Generate Code for Fuzzy System Using MATLAB Coder

You can generate code for evaluating a fuzzy inference system using MATLAB® Coder™. For more information on generating code, see “Code Generation” (MATLAB Coder).

To generate code for evaluating fuzzy systems, you must first create a fuzzy inference system (FIS). For more information, see “Build Fuzzy Systems at the Command Line” on page 2-31 and “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14.

While this example generates code for a type-1 Mamdani fuzzy inference system, the workflow also applies to Sugeno and type-2 fuzzy systems.

Generating code using MATLAB Coder does not support fuzzy FIS objects (`mamfis`, `sugfis`, `mamfistype2`, `sugfistype2`). To generate code for evaluating fuzzy systems, you must convert your fuzzy inference system objects into homogeneous structures using the `getFISCodeGenerationData` function.

Embed FIS Data in Generated Code

You can embed the data for your fuzzy inference system within the generated code. Use this option if you do not want to change the FIS data after compilation.

First, create a fuzzy system, or load a fuzzy system from a `.fis` file. For this example, load the fuzzy system from `tipper.fis`.

```
fisObject = readfis("tipper.fis");
```

To use this FIS for code generation, convert it to a homogeneous structure.

```
fis = getFISCodeGenerationData(fisObject);
```

By default, `getFISCodeGenerationData` assumes that the FIS object is a type-1 system. To generate code for a type-2 system, you must indicate the system type using `getFISCodeGenerationData(fisObject, "type2")`.

Create a function for evaluating the fuzzy system `fis` for a given input vector `x`. Within this function, you can specify options for the `evalfis` function using `evalfisOptions`.

```
function y = evaluatefis1(fis,x)
    %#codegen
    opt = evalfisOptions('NumSamplePoints',51);
    y = evalfis(fis,x,opt);
end
```

Generate code for `evaluatefis1`, specifying that the `fis` input argument is constant. You can specify different targets for your build, such as a static library, an executable, or a MEX file. For this example, generate a MEX file.

```
codegen('evaluatefis1','-args',{coder.Constant(fis),[0 0]},'-config:mex')
```

Code generation successful.

To verify the execution of the MEX file:

- 1 Evaluate the MEX file for one or more input values. When you call the MEX file, specify the same FIS structure that you used at compile time.

- 2 Evaluate the original FIS for the same input values using `evalfis`. When evaluating using `evalfis`, use the same homogeneous FIS structure.
- 3 Compare the evaluation results.

```
mexOutput1 = evaluatefis1_mex(fis,[7 9])
```

```
mexOutput1 = 21.0327
```

```
opt = evalfisOptions('NumSamplePoints',51);
evalfisOutput = evalfis(fis,[7 9],opt)
```

```
evalfisOutput = 21.0327
```

The MEX file output matches the `evalfis` output.

Alternatively, you can embed the FIS data in the generated code by reading the FIS data from a file at code generation time. Specify a function for evaluating a fuzzy system for given input vector `x`. Within this function, read the FIS data from the file `tipper.fis`.

```
function y = evaluatefis2(x)
    %#codegen
    fis = getFISCodeGenerationData('tipper.fis');
    opt = evalfisOptions('NumSamplePoints',51);
    y = evalfis(fis,x,opt);
end
```

Generate code for `evaluatefis2`.

```
codegen('evaluatefis2','-args',{[0 0]},'-config:mex')
```

Code generation successful.

Verify the execution of the MEX file using the same input values for `x`. In this case, you do not have to specify the original FIS structure used at compile time.

```
mexOutput2 = evaluatefis2_mex([7 9])
```

```
mexOutput2 = 21.0327
```

```
evalfisOutput
```

```
evalfisOutput = 21.0327
```

Generate Code for Loading FIS Data at Run Time

You can generate code for evaluating a FIS that is read from a `.fis` file specified at run time. In this case, the FIS data is not embedded in the generated code. Specify a function for evaluating the fuzzy system defined in the specified file `fileName` for a given input vector `x`.

```
function y = evaluatefis3(fileName,x)
    %#codegen
    fis = getFISCodeGenerationData(fileName);
    opt = evalfisOptions('NumSamplePoints',51);
    y = evalfis(fis,x,opt);
end
```

Define input data types for this function.

```
fileName = coder.newtype('char',[1 Inf],[false true]);
x = coder.newtype('double',[1 Inf],[false true]);
```

Generate code for `evaluatefis3`.

```
codegen('evaluatefis3','-args',{fileName,x},'-config:mex')
```

Code generation successful.

Verify the execution of the MEX file using the same input values for `x`. In this case, you specify the name of the `.fis` file.

```
mexOutput3 = evaluatefis3_mex('tipper.fis',[7 9])
```

```
mexOutput3 = 21.0327
```

```
evalfisOutput
```

```
evalfisOutput = 21.0327
```

Each time you run `evaluatefis3`, it reloads the fuzzy system from the file. For computational efficiency, you can create a function that only loads the FIS when a new file name is specified.

```
function y = evaluatefis4(fileName,x)
    %#codegen

    persistent fisName fis
    if isempty(fisName)
        [fisName,fis] = loadFIS(fileName);
    elseif ~strcmp(fisName,fileName)
        [fisName,fis] = loadFIS(fileName);
    end

    opt = evalfisOptions('NumSamplePoints',51);
    y = evalfis(fis,x,opt);
end

function [fisName,fis] = loadFIS(fileName)
    fisName = fileName;
    fis = getFISCodeGenerationData(fisName);
end
```

Generate code `evaluatefis4`. The input data types for this function are the same as for `evaluatefis3`.

```
codegen('evaluatefis4','-args',{fileName,x},'-config:mex')
```

Code generation successful.

Verify the execution of the MEX file using the same input values file name.

```
mexOutput4 = evaluatefis4_mex('tipper.fis',[7 9])
```

```
mexOutput4 = 21.0327
```

```
evalfisOutput
```

```
evalfisOutput = 21.0327
```

Generate Code for Single-Precision Data

The preceding examples generated code for double-precision data. To generate code for single-precision data, specify the data type of the input values as `single`. For example, generate code for `evaluatefis2` using single-precision data.

```
codegen('evaluatefis2','-args',{single([0 0])},'-config:mex')
```

Code generation successful.

Verify the MEX file execution, passing in single-precision input values.

```
mexOutputSingle = evaluatefis2_mex(single([7 9]))
```

```
mexOutputSingle = single  
                21.0327
```

```
evalfisOutput
```

```
evalfisOutput = 21.0327
```

See Also

`evalfis` | `getFISCodeGenerationData`

More About

- “Deploy Fuzzy Inference Systems” on page 6-2
- “Generate Code for Fuzzy System Using Simulink Coder” on page 6-3

Apps

Fuzzy Logic Designer

Design and test fuzzy inference systems

Description


The **Fuzzy Logic Designer** app lets you design and test fuzzy inference systems for modeling complex system behaviors.

Using this app, you can:

- Design Mamdani and Sugeno fuzzy inference systems.
- Add or remove input and output variables.
- Specify input and output membership functions.
- Define fuzzy if-then rules.
- Select fuzzy inference functions for:
 - And operations
 - Or operations
 - Implication
 - Aggregation
 - Defuzzification
- Adjust input values and view associated fuzzy inference diagrams.
- View output surface maps for fuzzy inference systems.
- Export fuzzy inference systems to the MATLAB workspace.

Limitations

The **Fuzzy Logic Designer** app does not support type-2 fuzzy systems.



Open the Fuzzy Logic Designer App

- MATLAB Toolstrip: On the **Apps** tab, under **Control System Design and Analysis**, click the app icon.
- MATLAB command prompt: Enter `fuzzyLogicDesigner`.

Examples

- “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14

Programmatic Use

`fuzzyLogicDesigner` opens the **Fuzzy Logic Designer** app.

`fuzzyLogicDesigner(fis)` opens the app and loads the fuzzy inference system `fis`. `fis` can be any `mamfis` or `sugfis` object in the MATLAB workspace.

`fuzzyLogicDesigner(fileName)` opens the app and loads a fuzzy inference system from a file. `fileName` is the name of a `.fis` file on the MATLAB path.

To save a fuzzy inference system to a `.fis` file:

- In **Fuzzy Logic Designer**, select **File > Export > To File**.
- At the command line, use `writeFIS`.

Compatibility Considerations

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

See Also

Apps

Neuro-Fuzzy Designer

Functions

`newfis` | `evalfis` | `plotfis` | `mfedit` | `ruleedit` | `ruleview` | `surfview`

Topics

“Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14

“What Is Fuzzy Logic?” on page 1-3

“Foundations of Fuzzy Logic” on page 1-7

“Fuzzy Inference Process” on page 1-19

Introduced in R2014b

Neuro-Fuzzy Designer

Design, train, and test Sugeno-type fuzzy inference systems

Description


The **Neuro-Fuzzy Designer** app lets you design, train, and test adaptive neuro-fuzzy inference systems (ANFIS) using input/output training data.

Using this app, you can:

- Tune membership function parameters of Sugeno-type fuzzy inference systems.
- Automatically generate an initial inference system structure based on your training data.
- Modify the inference system structure before tuning.
- Prevent overfitting to the training data using additional checking data.
- Test the generalization ability of your tuned system using testing data.
- Export your tuned fuzzy inference system to the MATLAB workspace.

You can use the **Neuro-Fuzzy Designer** to train a type-1 Sugeno-type fuzzy inference system that:

- Has a single output.
- Uses weighted average defuzzification.
- Has output membership functions all of the same type, for example `linear` or `constant`.
- Has complete rule coverage with no rule sharing; that is, the number of rules must match the number of output membership functions, and every rule must have a different consequent.
- Has unity weight for each rule.
- Does not use custom membership functions.



Open the Neuro-Fuzzy Designer App

- MATLAB Toolstrip: On the **Apps** tab, under **Control System Design and Analysis**, click the app icon.
- MATLAB command prompt: Enter `neuroFuzzyDesigner`.

Examples

- “Train Adaptive Neuro-Fuzzy Inference Systems” on page 3-177

Programmatic Use

`neuroFuzzyDesigner` opens the **Neuro-Fuzzy Designer** app.

`neuroFuzzyDesigner(fis)` opens the app and loads the fuzzy inference system `fis`. `fis` can be any valid `sugfis` object in the MATLAB workspace.

You can create an initial Sugeno-type fuzzy inference system from training data using the `genfis` command.

`neuroFuzzyDesigner(fileName)` opens the app and loads a fuzzy inference system. `fileName` is the name of a `.fis` file on the MATLAB path.

To save a fuzzy inference system to a `.fis` file:

- In the **Fuzzy Logic Designer**, select **File > Export > To File**
- At the command line, use `writeFIS`.

Compatibility Considerations

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

See Also

Apps

Fuzzy Logic Designer

Functions

`anfis` | `genfis`

Topics

“Train Adaptive Neuro-Fuzzy Inference Systems” on page 3-177

“Neuro-Adaptive Learning and ANFIS” on page 3-171

Introduced in R2014b

Functions

addInput

Add input variable to fuzzy inference system

Syntax

```
fisOut = addInput(fisIn)
fisOut = addInput(fisIn,range)
fisOut = addInput( ____,Name,Value)
```

Description

`fisOut = addInput(fisIn)` adds a default input variable to `fisIn` and returns the resulting fuzzy system in `fisOut`. This input variable has a default name, default range, and no membership functions.

`fisOut = addInput(fisIn, range)` adds an input variable with the specified range.

`fisOut = addInput(____, Name, Value)` configures the input variable using one or more name-value pair arguments.

Examples

Add Input Variable to Fuzzy Inference System

Create a Sugeno fuzzy inference system.

```
fis = sugfis('Name','tipper');
```

Add an input variable with default specifications.

```
fis = addInput(fis);
```

You can configure the input variable properties using dot notation. For example, specify the name and range for the variable.

```
fis.Inputs(1).Name = "service";
fis.Inputs(1).Range = [0 10];
```

View the input variable.

```
fis.Inputs(1)
```

```
ans =
  fisvar with properties:
      Name: "service"
      Range: [0 10]
  MembershipFunctions: [0x0 fismf]
```

You can also specify a variable name and range when you add it to the fuzzy system.

```

fis2 = sugfis('Name','tipper');
fis2 = addInput(fis2,[0 10],'Name','service');

```

Add Input Variable with Membership Functions

Create a fuzzy inference system.

```

fis = mamfis('Name','tipper');

```

Add an input variable with three Gaussian membership functions distributed over the input range.

```

fis = addInput(fis,'NumMFs',3,'MFTYPE','gaussmf');


```

View the membership functions.

```

plotmf(fis,'input',1)

```



Input Arguments

fisIn — Fuzzy inference system

mamfis object | sugfis object | mamfistype2 object | sugfistype2 object

Fuzzy inference system, specified as one of the following:

- `mamfis` object — Mamdani fuzzy inference system
- `sugfis` object — Sugeno fuzzy inference system
- `mamfistype2` object — Type-2 Mamdani fuzzy inference system
- `sugfistype2` object — Type-2 Sugeno fuzzy inference system

range — Variable range

[0 1] (default) | two-element vector

Variable range, specified as a two-element element vector where the first element is less than the second element. The first element specifies the lower bound of the range, and the second element specifies the upper bound of the range.

Name-Value Pair Arguments

Specify optional pairs of arguments as `Name1=Value1, ..., NameN=ValueN`, where `Name` is the argument name and `Value` is the corresponding value. Name-value arguments must appear after other arguments, but the order of the pairs does not matter.

Example: `fis = addInput(fis, NumMFs=3)`

Before R2021a, use commas to separate each name and value, and enclose Name in quotes.

Example: `fis = addInput(fis, 'NumMFs', 3)`

Name — Variable name

string | character vector

Variable name, specified as a string or character vector. The default variable name is `"input<uniqueIndex>"`, where `uniqueIndex` is automatically generated based on the current number of inputs in `fisIn`.

NumMFs — Number of membership functions

0 (default) | nonnegative integer

Number of membership functions, specified as a nonnegative integer.

MFType — Membership function type

"trimf" (default) | "gaussmf"

Membership function type, specified as one of the following values.

- `"trimf"` — Triangular membership functions
- `"gaussmf"` — Gaussian membership functions

The membership functions are uniformly distributed over the input variable range with approximately 80% overlap in the membership function supports.

Output Arguments**fisOut — Updated fuzzy inference system**

`mamfis` object | `sugfis` object | `mamfistype2` object | `sugfistype2` object

Updated fuzzy inference system, returned as one of the following objects.

- `mamfis` object — Mamdani fuzzy inference system
- `sugfis` object — Sugeno fuzzy inference system
- `mamfistype2` object — Type-2 Mamdani fuzzy inference system
- `sugfistype2` object — Type-2 Sugeno fuzzy inference system

`fisOut` contains the added input variable, with all other properties matching the properties of `fisIn`.

See Also

`removeInput` | `addOutput` | `fisvar`

Topics

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced in R2018b

addMF

Add membership function to fuzzy variable

Syntax

```
fisOut = addMF(fisIn,varName)
fisOut = addMF(fisIn,varName,type,parameters)
fisOut = addMF( __ ,Name,Value)

varOut = addMF(varIn)
varOut = addMF(varIn,type,parameters)
varOut = addMF( __ ,Name,Value)
```

Description

`fisOut = addMF(fisIn,varName)` adds a default membership function to the input or output variable `varName` in the fuzzy inference system `fisIn` and returns the resulting fuzzy system in `fisOut`.

`fisOut = addMF(fisIn,varName,type,parameters)` adds a membership function with the specified type and parameters.

`fisOut = addMF(__ ,Name,Value)` configures the membership function using one or more name-value pair arguments.

`varOut = addMF(varIn)` adds a default membership function to fuzzy variable `varIn` and returns the resulting fuzzy variable in `varOut`.

If `varIn` does not contain any membership functions, this syntax adds a default type-1 membership function. Otherwise, the type of the added membership function matches the type of the existing membership functions in `varIn`.

`varOut = addMF(varIn,type,parameters)` adds a membership function with the specified type and parameters.

`varOut = addMF(__ ,Name,Value)` specifies the name of the membership function using the `Name` name-value argument.

To add a type-2 membership function to a fuzzy variable with no existing membership functions, you must specify either the `LowerLag` or `LowerScale` name-value argument.

Examples

Add Membership Function to Fuzzy Inference System

Create a Mamdani fuzzy system, and add three input variables and one output variable. For this example, give the second input variable and the output variable the same name.

```
fis = mamfis;
fis = addInput(fis,[0 80],"Name","speed");
```

```

fis = addInput(fis,[0 100],"Name","throttle");
fis = addInput(fis,[0 10],"Name","distance");
fis = addOutput(fis,[0 100],"Name","throttle");

```

Add a membership function to the first input variable, specifying a trapezoidal membership function, and set the membership function parameters.

```

fis = addMF(fis,"speed","trapmf",[-5 0 10 30]);

```

You can also specify the name of your membership when you add it to a fuzzy system. Add a membership function called "high" to the first input variable.

```

fis = addMF(fis,"speed","trapmf",[50 70 80 85],'Name','high');


```

View the membership functions for the first input variable.

```

plotmf(fis,"input",1)

```




If your system has an input variable with the same name as an output variable, you must specify the variable type when adding a membership function. For example, add a membership function to the output variable.

```


fis = addMF(fis,"throttle","trimf",[0 20 40],'VariableType',"output");
plotmf(fis,"output",1)

```



Alternatively, you can add a default membership function to a fuzzy system and set its parameters using dot notation. For example, add and configure a membership function for the third input variable.

```
fis = addMF(fis,"distance");  
fis.Inputs(3).MembershipFunctions(1).Type = "trapmf";  
fis.Inputs(3).MembershipFunctions(1).Parameters = [-1 0 2 4];  
plotmf(fis,"input",3)
```



Add Membership Function to Type-2 Fuzzy Inference System

Create a type-2 Sugeno fuzzy system, and add two input variables and one output variable.

```
fis = sugfistype2;
fis = addInput(fis,[0 80],"Name","speed");
fis = addInput(fis,[0 10],"Name","distance");
fis = addOutput(fis,[0 100],"Name","braking");
```

Add a membership function to the first input variable, specifying a trapezoidal membership function, and set the membership function parameters. This type-2 membership function uses default lower membership function lag and scale parameters.

```
fis = addMF(fis,"speed","trapmf",[-5 0 10 30]);
```

You can also specify the configuration of the lower MF when adding a type-2 membership function.


```
fis = addMF(fis,"speed","trapmf",[10 30 50 70],'LowerScale',0.8,'LowerLag',0.1);
```

You can also specify the name of your membership function when you add it to a fuzzy system. Add a membership function called "high" to the first input variable.

```
fis = addMF(fis,"speed","trapmf",[50 70 80 85],'Name',"high");
```

View the membership functions for the first input variable.

```
plotmf(fis,"input",1)
```



Add Membership Function to Fuzzy Variable

Create a fuzzy variable with a specified range.

```
var = fisvar([0 1]);
```

Add a membership function to the variable, specifying a trapezoidal membership function, and set the membership function parameters.

```
var = addMF(var,"trapmf",[-0.5 0 0.2 0.4]);
```

You can also specify the name of your membership when you add it to a fuzzy variable. For example, add a membership function called "large".

```
var = addMF(var,"trapmf",[0.6 0.8 1 1.5],'Name',"large");
```

View the membership functions.

```
var.MembershipFunctions
```

```
ans =  
  1x2 fismf array with properties:
```

```
Type
Parameters
Name
```

Details:

	Name	Type	Parameters			
1	"mf1"	"trapmf"	-0.5	0	0.2	0.4
2	"large"	"trapmf"	0.6	0.8	1	1.5

Alternatively, you can add a default membership function to a fuzzy variable and set its parameters using dot notation.

```
var = fisvar([0 1]);
var = addMF(var);
var.MembershipFunctions(1).Type = "trapmf";
var.MembershipFunctions(1).Parameters = [-0.5 0 0.2 0.4];
```

Add Type-2 Membership Function to Fuzzy Variable

Create a fuzzy variable with a specified range. By default, this variable has no membership functions.

```
var = fisvar([0 9]);
```

To add a type-2 membership function to a variable with no existing membership functions, specify either a `LowerLag` or `LowerScale` value for the membership function. For example specify a lower scale value.

```
var = addMF(var, "trimf", [0 3 6], 'LowerScale', 1);
```

Once a variable contains a type-2 membership function, you can add additional type-2 membership functions without specifying one of these parameters.

```
var = addMF(var, "trimf", [3 6 9]);
```

View the membership functions.

```
var.MembershipFunctions
```

```
ans =
    1x2 fismftype2 array with properties:
```

```
Type
UpperParameters
LowerScale
LowerLag
Name
```

Details:

	Name	Type	Upper Parameters			Lower Scale	Lower Lag	
1	"mf1"	"trimf"	0	3	6	1	0.2	0.2

2 "mf2" "trimf" 3 6 9 1 0.2 0.2

Input Arguments

fisIn — Fuzzy inference system

mamfis object | sugfis object | mamfistype2 object | sugfistype2 object

Fuzzy inference system, specified as one of the following:

- **mamfis** object — Mamdani fuzzy inference system
- **sugfis** object — Sugeno fuzzy inference system
- **mamfistype2** object — Type-2 Mamdani fuzzy inference system
- **sugfistype2** object — Type-2 Sugeno fuzzy inference system

varName — Variable name

string | character vector

Variable name, specified as a string or character vector. You can specify the name of either an input or output variable in your FIS. If your system has an input variable with the same name as an output variable, specify the type of the variable you want to add a membership function to using the `VariableType` name-value pair.

type — Membership function type

"trimf" (default) | string | character vector | function handle

Membership function type, specified as a string or character vector that contains the name of a function in the current working folder or on the MATLAB path. You can also specify a handle to such a function. When you specify `type`, you must also specify `parameters`.

This table describes the values that you can specify for `type`.

Membership Function Type	Description	For More Information
"gbellmf"	Generalized bell-shaped membership function	gbellmf
"gaussmf"	Gaussian membership function	gaussmf
"gauss2mf"	Gaussian combination membership function	gauss2mf
"trimf"	Triangular membership function	trimf
"trapmf"	Trapezoidal membership function	trapmf
"linsmf"	Linear s-shaped saturation membership function	linsmf
"linzmf"	Linear z-shaped saturation membership function	linzmf
"sigmf"	Sigmoidal membership function	sigmf

Membership Function Type	Description	For More Information
"dsigmf"	Difference between two sigmoidal membership functions	dsigmf
"psigmf"	Product of two sigmoidal membership functions	psigmf
"zmf"	Z-shaped membership function	zmf
"pimf"	Pi-shaped membership function	pimf
"smf"	S-shaped membership function	smf
"constant"	Constant membership function for Sugeno output membership functions	"Sugeno Fuzzy Inference Systems" on page 2-3
"linear"	Linear membership function for Sugeno output membership functions	
String or character vector	Name of a custom membership function in the current working folder or on the MATLAB path. Custom output membership functions are not supported for Sugeno systems.	"Build Fuzzy Systems Using Custom Functions" on page 2-40
Function handle	Handle to a custom membership function in the current working folder or on the MATLAB path. Custom output membership functions are not supported for Sugeno systems.	

parameters — Membership function parameters

[0 0.5 1] (default) | vector

Membership function parameters, specified as a vector. The length of the parameter vector depends on the membership function type. When you specify `parameters`, you must also specify `type`.

When `fisIn` is a type-1 FIS or `varIn` contains type-1 membership functions, `parameters` sets the `Parameters` property of the added membership function.

When `fisIn` is a type-2 FIS or `varIn` contains type-2 membership functions, `parameters` sets the `UpperParameters` property of the added membership function.

varIn — Fuzzy variable

`fisvar` object

Fuzzy variable, specified as a `fisvar` object.

Name-Value Pair Arguments

Specify optional pairs of arguments as `Name1=Value1, ..., NameN=ValueN`, where `Name` is the argument name and `Value` is the corresponding value. Name-value arguments must appear after other arguments, but the order of the pairs does not matter.

Example: `fis = addMF(fis, "distance", Name="high")`

Before R2021a, use commas to separate each name and value, and enclose Name in quotes.

Example: `fis = addMF(fis,"distance","Name","high")`

Name — Membership function name

string | character vector

Membership function name, specified as the comma-separated pair consisting of 'Name' and a string or character vector. The default membership function name is "mf<uniqueIndex>", where `uniqueIndex` is automatically generated based on the current number of membership functions in the associated variable.

VariableType — Variable type

"input" | "output"

Variable type, specified as the comma-separated pair 'VariableType' and one of the following:

- "input" — Input variable
- "output" — Output variable

If your system has an input variable with the same name as an output variable, specify which variable to add the membership function to `VariableType`.

This name-value pair does not apply when adding when adding a membership function to a `fisvar` object.

LowerScale — Lower membership function scaling factor

1 (default) | positive scalar less than or equal to 1

Lower membership function scaling factor for type-2 membership functions, specified as a positive scalar less than or equal to 1. Use `LowerScale` to define the maximum value of the lower membership function.

Depending on the value of `LowerLag`, the actual maximum lower membership function value can be less than `LowerScale`.

This name-value pair applies only when adding type-2 membership functions.

LowerLag — Lower membership function delay factor

[0.2 0.2] (default) | scalar value between 0 and 1 | vector of length 2

Lower membership function delay factor for type-2 membership functions, specified as a scalar value or a vector of length two. You can specify lag values between 0 and 1, inclusive.

This name-value pair applies only when adding type-2 membership functions.

The following membership function types support only a scalar `LowerLag` value:

- Symmetric MFs — `gaussmf` and `gbellmf`
- One-sided MFs — `sigmf`, `smf`, and `zmf`

All other built-in membership functions support either a scalar or vector `LowerLag` value. For these membership functions, when you specify a:

- Scalar value, the same lag value is used for both the left and right side of the membership function.

- Vector value, you can define different lag values for the left and right sides of the membership function.

The lag value defines the point at which the lower membership function value starts increasing from zero based on the value of the upper membership function. For example, a lag value of 0.1 indicates that the lower membership function becomes positive when the upper membership function has a membership value of 0.1 .

When the lag value is zero, the lower membership function starts increasing at the same point as the upper membership function.

Some membership function types restrict the maximum lag value. For example, `LowerLag` must be less than 1 for the `gaussmf`, `gauss2mf`, `gbellmf`, `sigmf`, `dsigmf`, and `psigmf` membership functions.

Output Arguments

fisOut — Fuzzy inference system

`mamfis` object | `sugfis` object | `mamfistype2` object | `sugfistype2` object

Fuzzy inference system, specified as one of the following:

- `mamfis` object — Mamdani fuzzy inference system
- `sugfis` object — Sugeno fuzzy inference system
- `mamfistype2` object — Type-2 Mamdani fuzzy inference system
- `sugfistype2` object — Type-2 Sugeno fuzzy inference system

`fisOut` contains the added membership function, with all other properties matching the properties of `fisIn`. `fisInfisOut` contains the added membership function, with all other properties matching the properties of `fisIn`.

varOut — Fuzzy variable

`fisvar` object

Fuzzy variable, returned as a `fisvar` object. `varOut` contains the added membership function, with all other properties matching the properties of `varIn`.

Compatibility Considerations

addmf is now addMF and its function syntax has changed

Behavior changed in R2018b

The name and behavior of the `addmf` function has changed. Now:

- `addmf` is `addMF`
- You specify the variable to which you want to add the membership function by name rather than by index.
- You specify the name of the membership function using a name-value pair argument.

These changes require updates to your code.

Update Code

The following table shows some typical usages of `addmf` for adding membership functions to fuzzy variables and how to update your code. In this table, `fis` is a fuzzy inference system with two inputs, `service` and `food`, and one output, `tip`.

If your code has this form:	Use this code instead:
<code>fis = addmf(fis,'input',1,... 'poor',... 'gaussmf',[1.5 0])</code>	<code>fis = addMF(fis,"service",... "gaussmf",[1.5 0], 'Name',"poor")</code>
<code>fis = addmf(fis,'input',2,... 'rancid',... 'trapmf',[-2 0 1 3])</code>	<code>fis = addMF(fis,"food",... "trapmf",[-2 0 1 3],... 'Name',"rancid")</code>
<code>fis = addmf(fis,'output',1,... 'cheap',... 'trimf',[0 5 10])</code>	<code>fis = addMF(fis,"tip",... "trimf",[0 5 10],... 'Name',"cheap")</code>

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

See Also

`mamfis` | `sugfis` | `fisvar` | `removeMF` | `addInput` | `addOutput` | `addRule`

Topics

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced in R2018b

addOutput

Add output variable to fuzzy inference system

Syntax

```

fisOut = addOutput(fisIn)
fisOut = addOutput(fisIn,range)
fisOut = addOutput( ___,Name,Value)

```

Description

`fisOut = addOutput(fisIn)` adds a default output variable to `fisIn`, and returns the resulting fuzzy system in `fisOut`. This output variable has a default name, default range, and no membership functions.

`fisOut = addOutput(fisIn, range)` adds an output variable with the specified range.

`fisOut = addOutput(___, Name, Value)` configures the output variable using one or more name-value pair arguments.

Examples

Add Output Variable to Fuzzy Inference System

Create a Mamdani fuzzy inference system.

```

fis = mamfis('Name','tipper');

```

Add an output variable with default specifications.

```

fis = addOutput(fis);

```

You can configure the output variable properties using dot notation. For example, specify the name and range for the variable.

```

fis.Outputs(1).Name = "tip";
fis.Outputs(1).Range = [10 30];

```

View the output variable.

```

fis.Outputs(1)

ans =
    fisvar with properties:
        Name: "tip"
        Range: [10 30]
        MembershipFunctions: [0x0 fismf]

```

You can also specify the variable name and range when you add it to the fuzzy system.

```

fis2 = mamfis('Name','tipper');
fis2 = addOutput(fis2,[10 30],'Name','tip');

```

Add Output Variable with Membership Functions

Create a Sugeno fuzzy inference system.

```

fis = sugfis('Name','tipper');

```

Add an output variable with three constant membership functions distributed over the output range.

```

fis = addOutput(fis,'NumMFs',3,'MFTType','constant');

```

View the membership functions.

```

fis.Outputs(1).MembershipFunctions

```

```

ans =
    1x3 fismf array with properties:

```

```

    Type
    Parameters
    Name

```

Details:

	Name	Type	Parameters
1	"mf1"	"constant"	0
2	"mf2"	"constant"	0.5
3	"mf3"	"constant"	1

Input Arguments

fisIn — Fuzzy inference system

mamfis object | sugfis object | mamfistype2 object | sugfistype2 object

Fuzzy inference system, specified as one of the following objects.

- mamfis object — Mamdani fuzzy inference system
- sugfis object — Sugeno fuzzy inference system
- mamfistype2 object — Type-2 Mamdani fuzzy inference system
- sugfistype2 object — Type-2 Sugeno fuzzy inference system

range — Variable range

[0 1] (default) | two-element vector

Variable range, specified as a two-element element vector where the first element is less than the second element. The first element specifies the lower bound of the range, and the second element specifies the upper bound of the range.

Name-Value Pair Arguments

Specify optional pairs of arguments as `Name1=Value1, ..., NameN=ValueN`, where `Name` is the argument name and `Value` is the corresponding value. Name-value arguments must appear after other arguments, but the order of the pairs does not matter.

Example: `fis = addOutput(fis, NumMFs=3)`

Before R2021a, use commas to separate each name and value, and enclose Name in quotes.

Example: `fis = addOutput(fis, 'NumMFs', 3)`

Name — Variable name

string | character vector

Variable name, specified as a string or character vector.

NumMFs — Number of membership functions

0 (default) | nonnegative integer

Number of membership functions, specified as a nonnegative integer.

MFType — Membership function type

"trimf" (default) | "gaussmf"

Membership function type, specified as one of the following values.

- "trimf" — Triangular membership functions for the outputs of Mamdani system
- "gaussmf" — Gaussian membership functions for the outputs of Mamdani systems
- "constant" — Constant membership functions for the outputs of Sugeno systems
- "linear" — Linear membership functions for the outputs of Sugeno systems. To add an output variable with linear membership functions, your FIS must have at least one input variable.

The membership functions are uniformly distributed over the variable range with approximately 80% overlap in the membership function supports.

Output Arguments

fisOut — Updated fuzzy inference system

mamfis object | sugfis object | mamfistype2 object | sugfistype2 object

Updated inference system, returned as one of the following objects.

- mamfis object — Mamdani fuzzy inference system
- sugfis object — Sugeno fuzzy inference system
- mamfistype2 object — Type-2 Mamdani fuzzy inference system
- sugfistype2 object — Type-2 Sugeno fuzzy inference system

`fisOut` contains the added output variable, with all other properties matching the properties of `fisIn`.

See Also

`removeOutput` | `addInput` | `fisvar`

Topics

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced in R2018b

addRule

Add rule to fuzzy inference system

Syntax

```
fisOut = addRule(fisIn)
fisOut = addRule(fisIn,ruleDescription)
```

Description

`fisOut = addRule(fisIn)` adds a single fuzzy rule to fuzzy inference system `fisIn` with the default description "input1==mf1 => output1=mf1" and returns the resulting fuzzy system in `fisOut`.

`fisOut = addRule(fisIn,ruleDescription)` adds one or more fuzzy rules using the rule descriptions in `ruleDescription`.

Examples

Add Single Rule to Fuzzy Inference System

Load a fuzzy inference system (FIS), and clear the existing rules.

```
fis = readfis('tipper');
fis.Rules = [];
```

Add a rule to the FIS.

```
ruleTxt = 'If service is poor then tip is cheap';
fis2 = addRule(fis,ruleTxt);
```

`fis2` is equivalent to `fis`, except that the specified rule is added to the rule base.

`fis2.Rules`

```
ans =
  fisrule with properties:
    Description: "service==poor => tip=cheap (1)"
    Antecedent: [1 0]
    Consequent: 1
    Weight: 1
    Connection: 1
```

Add Rules to Fuzzy Inference System

Load a fuzzy inference system (FIS).

```
fis = readfis('tipper');
```

Specify if-then rules using linguistic expressions.

```
rule1 = "If service is poor or food is rancid then tip is cheap";
rule2 = "If service is excellent and food is not rancid then tip is generous";
rules = [rule1 rule2];
```

Add the rules to the FIS.

```
fis2 = addRule(fis,rules);
```

`fis2` is equivalent to `fis`, except that the specified rules are added to the rule base.

Add Rules Using Symbolic Expressions

Load a fuzzy inference system (FIS), and clear the existing rules.

```
fis = readfis('tipper');
fis.Rules = [];
```

Specify the following rules using symbolic expressions:

- If service is poor or food is rancid then tip is cheap.
- If service is excellent and food is not rancid then tip is generous.

```
rule1 = "service==poor | food==rancid => tip=cheap";
rule2 = "service==excellent & food~=rancid => tip=generous";
rules = [rule1 rule2];
```

Add the rules to the FIS.

```
fis2 = addRule(fis,rules);
```

`fis2` is equivalent to `fis`, except that the specified rules are added to the rule base.

```
fis2.Rules
```

```
ans =
    1x2 fisrule array with properties:
```

```
    Description
    Antecedent
    Consequent
    Weight
    Connection
```

```
Details:
```

```
Description
```

```

1  "service==poor | food==rancid => tip=cheap (1)"
2  "service==excellent & food~=rancid => tip=generous (1)"
```

Add Rules Using Membership Function Indices

Load fuzzy inference system (FIS) and clear the existing rules.

```
fis = readfis('mam22.fis');
fis.Rules = [];
```

Specify the following rules using membership function indices:

- If angle is small and velocity is big, then force is negBig and force2 is posBig2.
- If angle is not small and velocity is small, then force is posSmall and force2 is negSmall2.

```
rule1 = [1 2 1 4 1 1];
rule2 = [-1 1 3 2 1 1];
rules = [rule1; rule2];
```

Add the rules to the FIS.

```
fis2 = addRule(fis,rules);
```

fis2 is equivalent to fis, except that the specified rules are added to the rule base.

fis2.Rules

```
ans =
  1x2 fisrule array with properties:
```

```
  Description
  Antecedent
  Consequent
  Weight
  Connection
```

Details:

Description

```
 1 "angle==small & velocity==big => force=negBig, force2=posBig2 (1)"
 2 "angle~=small & velocity==small => force=posSmall, force2=negSmall2 (1)"
```

Input Arguments

fisIn — Fuzzy inference system

mamfis object | sugfis object | mamfistype2 object | sugfistype2 object

Fuzzy inference system, specified as one of the following objects.

- mamfis object — Mamdani fuzzy inference system
- sugfis object — Sugeno fuzzy inference system
- mamfistype2 object — Type-2 Mamdani fuzzy inference system

- `sugfistype2` object — Type-2 Sugeno fuzzy inference system

ruleDescription — Rule description

string | character vector | numeric row vector | string array | character array | numeric array

Rule description, specified using either a text or numeric rule definition

Text Rule Description

For a text rule description, specify `ruleDescription` as one of the following:

- String or character vector specifying a single rule.

```
rule = "If service is poor or food is rancid then tip is cheap";
```

- String array, where each element corresponds to a rule.

```
ruleList = ["If service is poor or food is rancid then tip is cheap";  
           "If service is good then tip is average";  
           "If service is excellent or food is delicious then tip is generous"];
```

- Character array where each row corresponds to a rule.

```
rule1 = 'If service is poor or food is rancid then tip is cheap';  
rule2 = 'If service is good then tip is average';  
rule3 = 'If service is excellent or food is delicious then tip is generous';  
ruleList = char(rule1,rule2,rule3);
```

For each rule, use one of the following rule text formats.

- Verbose — Linguistic expression in the following format, using the IF and THEN keywords:

```
"IF <antecedent> THEN <consequent> (<weight>)"
```

In `<antecedent>`, specify the membership function for each input variable using the IS or IS NOT keyword. Connect these conditions using the AND or OR keywords. If a rule does not use a given input variable, omit it from the antecedent.

In `<consequent>`, specify the condition for each output variable using the IS or IS NOT keyword, and separate these conditions using commas. The IS NOT keyword is not supported for Sugeno outputs. If a rule does not use a given output variable, omit it from the consequent.

Specify the weight using a positive numerical value.

```
"IF A IS a AND B IS NOT b THEN X IS x, Y IS NOT y (1)"
```

- Symbolic — Expression that uses the symbols in the following table instead of keywords. There is no symbol for the IF keyword.

Symbol	Keyword
==	IS (in rule antecedent)
~=	IS NOT
&	AND
	OR
=>	THEN
=	IS (in rule consequent)

For example, the following symbolic rule is equivalent to the previous verbose rule.

```
"A==a & B~=b => X=x, Y~=y (1)"
```

Numeric Rule Description

For a numeric rule description, specify `ruleDescription` as one of the following:

- Row vector to specify a single fuzzy rule
- Array, where each row of `ruleValues` specifies one rule

For each row, the numeric rule description has $M+N+2$ columns, where M is the number of input variables and N is the number of output variables. Each column contains the following information:

- The first M columns specify input membership function indices and correspond to the Antecedent property of the rule. To indicate a NOT condition, specify a negative value. If a rule does not use a given input, set the corresponding index to 0. For each rule, at least one input membership function index must be nonzero.
- The next N columns specify output membership function indices and correspond to the Consequent property of the rule. To indicate a NOT condition for Mamdani systems, specify a negative value. NOT conditions are not supported for Sugeno outputs. If a rule does not use a given output, set the corresponding index to 0. For each rule, at least one output membership function index must be nonzero.
- Column $M+N+1$ specifies the rule weight and corresponds to the `Weight` property of the rule.
- The final column specifies the antecedent fuzzy operator and corresponds to the `Connection` property of the rule.

Output Arguments

fisOut — Updated fuzzy inference system

`mamfis` object | `sugfis` object | `mamfistype2` object | `sugfistype2` object

Updated fuzzy inference system, returned as one of the following objects.

- `mamfis` object — Mamdani fuzzy inference system
- `sugfis` object — Sugeno fuzzy inference system
- `mamfistype2` object — Type-2 Mamdani fuzzy inference system
- `sugfistype2` object — Type-2 Sugeno fuzzy inference system

`fisOut` contains the added output rules, with all other properties matching the properties of `fisIn`.

Compatibility Considerations

addrule is now **addRule**

Behavior changed in R2018b

`addrule` is now `addRule`. To update your code, change the function name from `addrule` to `addRule`. The syntaxes are equivalent.

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

See Also

`addInput` | `addOutput` | `addMF`

Topics

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced in R2018b

addvar

(To be removed) Add variable to fuzzy inference system

Note addvar will be removed in a future release. Use addInput or addOutput instead. For more information, see “Compatibility Considerations”.

Syntax

```
outfis = addvar(infis,varType,varName,varRange)
```

Description

`outfis = addvar(infis,varType,varName,varRange)` adds an input or output variable to the fuzzy system `infis` with the specified name and range.

Indices are applied to variables in the order in which they are added. For example, the first input variable added to a system is input variable number one for that system. Input and output variables are numbered independently.

Examples

Add Variable to Fuzzy Inference System

Create a new FIS.

```
fis = newfis('tipper');
```

Add a new input variable.

```
fis = addvar(fis,'input','service',[0 10]);
```

View new variable properties.

```
getfis(fis,'input',1)
```

```
ans = struct with fields:
    Name: 'service'
    NumMFs: 0
    range: [0 10]
```

Input Arguments

infis — Fuzzy system

mamfis object | sugfis object

Fuzzy system, specified as a FIS object.

varType — Variable type

'input' | 'output'

Variable type, specified as either 'input' or 'output'.

varName — Variable name

string | character vector

Variable name, specified as a string or character vector.

varRange — Variable range

two-element vector

Variable range, specified as a two-element vector, where the first element is the minimum value and the second element is the maximum value for the variable.

Output Arguments

outfis — Updated fuzzy system

mamfis object | sugfis object

Updated fuzzy system, returned as a FIS object.

Compatibility Considerations

addvar will be removed*Not recommended starting in R2018b*

addvar will be removed in a future release. To add input or output variables to a fuzzy system, use addInput or addOutput, respectively, instead. There are differences between these functions that require updates to your code.

Update Code

This table shows some typical usages of addvar and how to update your code to use addInput or addOutput instead.

If your code has this form:	Use this code instead:
<pre>fis = addvar(fis,'input',... 'service',[0 10])</pre>	<pre>fis = addInput(fis,[0 10],... 'Name',"service")</pre>
<pre>fis = addvar(fis,'output',... 'tip',[0 30])</pre>	<pre>fis = addOutput(fis,[0 30],... 'Name',"tip")</pre>

See Also

addInput | addOutput | addMF | addRule | rmmf | rmvar

Introduced before R2006a

anfis

Tune Sugeno-type fuzzy inference system using training data

Syntax

```

fis = anfis(trainingData)
fis = anfis(trainingData,options)

[fis,trainError] = anfis( ___ )
[fis,trainError,stepSize] = anfis( ___ )

[fis,trainError,stepSize,chkFIS,chkError] = anfis(trainingData,options)

```

Description

`fis = anfis(trainingData)` generates a single-output Sugeno fuzzy inference system (FIS) and tunes the system parameters using the specified input/output training data. The FIS object is automatically generated using grid partitioning.

The training algorithm uses a combination of the least-squares and backpropagation gradient descent methods to model the training data set.

`fis = anfis(trainingData,options)` tunes an FIS using the specified training data and options. Using this syntax, you can specify:

- An initial FIS object to tune.
- Validation data for preventing overfitting to training data.
- Training algorithm options.
- Whether to display training progress information.

`[fis,trainError] = anfis(___)` returns the root mean square training error for each training epoch.

`[fis,trainError,stepSize] = anfis(___)` returns the training step size at each training epoch.

`[fis,trainError,stepSize,chkFIS,chkError] = anfis(trainingData,options)` returns the validation data error for each training epoch, `chkError`, and the tuned FIS object for which the validation error is minimum, `chkFIS`. To use this syntax, you must specify validation data using `options.ValidationData`.

Examples

Train Fuzzy Inference System Using ANFIS

Load training data. This data has a single input and a single output.

```
load fuzex1trnData.dat
```

Generate and train a fuzzy inference system. By default, the FIS structure is created using a grid partition of the input variable range with two membership functions.

```
fis = anfis(fuzex1trnData);
```

```
ANFIS info:
```

```
  Number of nodes: 12  
  Number of linear parameters: 4  
  Number of nonlinear parameters: 6  
  Total number of parameters: 10  
  Number of training data pairs: 25  
  Number of checking data pairs: 0  
  Number of fuzzy rules: 2
```

```
Start training ANFIS ...
```


```
1      0.229709  
2      0.22896  
3      0.228265  
4      0.227624  
Step size increases to 0.011000 after epoch 5.  
5      0.227036  
6      0.2265  
7      0.225968  
8      0.225488  
Step size increases to 0.012100 after epoch 9.  
9      0.225052  
10     0.22465
```

```
Designated epoch number reached. ANFIS training completed at epoch 10.
```

```
Minimal training RMSE = 0.22465
```

```
Plot the ANFIS output and training data.
```

```
x = fuzex1trnData(:,1);  
anfisOutput = evalfis(fis,x);  
plot(x,fuzex1trnData(:,2),'*r',x,anfisOutput,'.b')  
legend('Training Data','ANFIS Output','Location','NorthWest')
```



The ANFIS data does not match the training data well. To improve the match:

- Increase the number of membership functions in the FIS structure to 4. Doing so adds fuzzy rules and tunable parameters to the system.
- Increase the number of training epochs.

```
opt = anfisOptions('InitialFIS',4,'EpochNumber',40);
```

Suppress the error and step size Command Window display.

```
opt.DisplayErrorValues = 0;
opt.DisplayStepSize = 0;
```

Train the FIS.

```
fis = anfis(fuzex1trnData,opt);
```


ANFIS info:

```
Number of nodes: 20
Number of linear parameters: 8
Number of nonlinear parameters: 12
Total number of parameters: 20
Number of training data pairs: 25
Number of checking data pairs: 0
Number of fuzzy rules: 4
```

Minimal training RMSE = 0.0833853

Plot the ANFIS output and training data.

```
figure
anfisoOutput = evalfis(fis,x);
plot(x,fuzexltrnData(:,2),'*r',x,anfisoOutput,'.b')
legend('Training Data','ANFIS Output','Location','NorthWest')
```



The match between the training data and ANFIS output has improved.

Create Initial FIS for ANFIS Training

Create single-input, single-output training data.

```
x = (0:0.1:10)';
y = sin(2*x)./exp(x/5);
```

Define an initial FIS structure with five Gaussian input membership functions.

```
genOpt = genfisOptions('GridPartition');
genOpt.NumMembershipFunctions = 5;
genOpt.InputMembershipFunctionType = 'gaussmf';
inFIS = genfis(x,y,genOpt);
```

Configure the ANFIS training options. Set the initial FIS, and suppress the training progress display.

```

opt = anfisOptions('InitialFIS',inFIS);
opt.DisplayANFISInformation = 0;
opt.DisplayErrorValues = 0;
opt.DisplayStepSize = 0;
opt.DisplayFinalResults = 0;

```

Train the FIS using the specified options.


```
outFIS = anfis([x y],opt);
```

Compare the ANFIS output with the training data.

```

plot(x,y,x,evalfis(outFIS,x))
legend('Training Data','ANFIS Output')

```



Obtain ANFIS Training Error

Load training data. This data has a single input and a single output.

```
load fuzex2trnData.dat
```

Specify the training options.

```

opt = anfisOptions('InitialFIS',4,'EpochNumber',40);
opt.DisplayANFISInformation = 0;

```

```
opt.DisplayErrorValues = 0;  
opt.DisplayStepSize = 0;  
opt.DisplayFinalResults = 0;
```

Train the FIS, and return the training error.

```
[fis,trainError] = anfis(fuzex2trnData,opt);
```

`trainError` contains the root mean squared error for the training data at each training epoch. The training error for `fis` is the minimum value in `trainError`.

```
fisRMSE = min(trainError)
```

```
fisRMSE = 0.2572
```

Obtain ANFIS Step Size Profile

Create single-input, single-output training data.

```
x = (0:0.1:10)';  
y = sin(2*x)./exp(x/5);
```

Configure the ANFIS training options. Set the initial FIS, and suppress the training progress display.

```
opt = anfisOptions('InitialFIS',4,'EpochNumber',60);  
opt.DisplayANFISInformation = 0;  
opt.DisplayErrorValues = 0;  
opt.DisplayStepSize = 0;  
opt.DisplayFinalResults = 0;
```

A larger step size increase rate can make the training converge faster. However, increasing the step size increase rate too much can lead to poor convergence. For this example, try doubling the step size increase rate.


```
opt.StepSizeIncreaseRate = 2*opt.StepSizeIncreaseRate;
```

Train the FIS, and return the step size array.

```
[fis,~,stepSize] = anfis([x y],opt);
```

Plot the step size profile. An optimal step size profile should increase initially, reach a maximum, and then decrease for the rest of the training.

```
figure  
plot(stepSize)
```



Validate ANFIS Training

Load training data.

```
load fuzex1trnData.dat
```

Load validation data.

```
load fuzex1chkData.dat
```

Specify the following training options:

- 4 input membership functions
- 30 training epochs
- Suppress training progress display

```
opt = anfisOptions('InitialFIS',4,'EpochNumber',30);
opt.DisplayANFISInformation = 0;
opt.DisplayErrorValues = 0;
opt.DisplayStepSize = 0;
opt.DisplayFinalResults = 0;
```

Add the validation data to the training options.


```
opt.ValidationData = fuzex1chkData;
```

Train the FIS, and return the validation results.

```
[fis,trainError,stepSize,chkFIS,chkError] = anfis(fuzex1trnData,opt);
```

The training error, `trainError`, and validation error, `chkError`, arrays each contain one error value per training epoch. Plot the training error and the validation error.

```
x = [1:30];
plot(x,trainError,'.b',x,chkError,'*r')
```



The minimum validation error occurs at epoch 17. The increase in validation error after this point indicates overfitting of the model parameters to the training data. Therefore, the tuned FIS at epoch 17, `chkFIS`, exhibits the best generalization performance.

Input Arguments

trainingData — Training data

array

Training data, specified as an array. For a fuzzy system with N inputs, specify `trainingData` as an array with $N+1$ columns. The first N columns contain input data, and the final column contains output data. Each row of `trainingData` contains one data point.

Generally, training data should fully represent the features of the data the FIS is intended to model.

options — Training options

`anfisOptions` option set

Training options, specified as an `anfisOptions` option set. Using `options`, you can specify:

- An initial FIS structure to tune, `options.InitialFIS`.
- Validation data for preventing overfitting to training data, `options.ValidationData`.
- Training algorithm options, such as the maximum number of training epochs, `options.EpochNumber`, or the training error goal, `options.ErrorGoal`.
- Whether to display training progress information, such as the training error values for each training epoch, `options.DisplayErrorValues`.

Output Arguments**fis — Trained fuzzy inference system**

`mamfis` object | `sugfis` object

Trained fuzzy inference system with membership function parameters tuned using the training data, returned as a `mamfis` or `sugfis` object. This fuzzy system corresponds to the epoch for which the training error is smallest. If two epochs have the same minimum training error, the FIS from the earlier epoch is returned.

trainError — Root mean square training error

array

Root mean square training error for each training epoch, returned as an array. The minimum value in `trainError` is the training error for fuzzy system `fis`.

stepSize — Training step size

array

Training step size for each epoch, returned as an array. The `anfis` training algorithm tunes the FIS parameters using gradient descent optimization methods. The training step size is the magnitude of the gradient transitions in the parameter space.

Ideally, the step size increases at the start of training, reaches a maximum, and then decreases for the remainder of the training. To achieve this step size profile, adjust the initial step size (`options.InitialStepSize`), step size increase rate (`options.StepSizeIncreaseRate`), and step size decrease rate `options.StepSizeDecreaseRate`.

chkFIS — Tuned FIS for which the validation error is minimum

`mamfis` object | `sugfis` object

Tuned FIS for which the validation error is minimum, returned as a `mamfis` or `sugfis` object. If two epochs have the same minimum validation error, the FIS from the earlier epoch is returned.

`chkFIS` is returned only when you specify validation data using `options.ValidationData`.

chkError — Root mean square validation error

array

Root mean square training error, returned as an array with length equal to the number of training epochs. The minimum value in `chkError` is the training error for fuzzy system `chkFIS`.

chkError is returned only when you specify validation data using `options.ValidationData`.

Alternative Functionality

tunefis Function

Starting in R2019a, you can tune a fuzzy system using `tunefis`. This function provides several other options for tuning algorithms, specified by the `tunefisOptions` object.

To use ANFIS, specify the tuning algorithm as "anfis" in `tunefisOptions`. Then, use the options object as an input argument for `tunefis`. For example:

Create the initial fuzzy inference system, and define the tunable parameter settings.

```
x = (0:0.1:10)';
y = sin(2*x)./exp(x/5);
options = genfisOptions('GridPartition');
options.NumMembershipFunctions = 5;
fisin = genfis(x,y,options);
[in,out,rule] = getTunableSettings(fisin);
```

Tune the membership function parameters with "anfis".

```
opt = tunefisOptions("Method","anfis");
fisout = tunefis(fisin,[in;out],x,y,opt);
```

Compatibility Considerations

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

References

- [1] Jang, J.-S. R., "Fuzzy Modeling Using Generalized Neural Networks and Kalman Filter Algorithm," *Proc. of the Ninth National Conf. on Artificial Intelligence (AAAI-91)*. July 1991, pp. 762-767.
- [2] Jang, J.-S. R., "ANFIS: Adaptive-Network-based Fuzzy Inference Systems," *IEEE Transactions on Systems, Man, and Cybernetics*, Vol. 23, No. 3, May 1993, pp. 665-685.

See Also

Apps

Neuro-Fuzzy Designer

Functions

anfisOptions | genfis | tunefis

Topics

“Neuro-Adaptive Learning and ANFIS” on page 3-171

“Predict Chaotic Time-Series Using ANFIS” on page 3-193

“Modeling Inverse Kinematics in a Robotic Arm” on page 3-201

Introduced before R2006a

convertfis

Convert previous versions of fuzzy inference data in current format

Syntax

```
fisNew = convertfis(fisOld)
```

Description

In R2018b, the format of fuzzy inference systems changed from a structure format to an object format. To convert fuzzy systems in an old format to the new format, use `convertfis`.

`fisNew = convertfis(fisOld)` converts the old-format fuzzy inference system `fisOld` into the current object format.

Examples

Convert Old-Format Fuzzy Inference System

Load a fuzzy inference system created using an old format. For example, load a FIS structure from a MAT-file.

```
load fisStructure
```

View the fields of the structure.

```
fisStructure
```

```
fisStructure = struct with fields:
    name: 'tipper'
    type: 'mamdani'
    andMethod: 'min'
    orMethod: 'max'
    defuzzMethod: 'centroid'
    impMethod: 'min'
    aggMethod: 'max'
    input: [1x2 struct]
    output: [1x1 struct]
    rule: [1x3 struct]
```

Convert the structure to a `mamfis` object and view the object properties.

```
fisObject = convertfis(fisStructure)
```

```
fisObject =
    mamfis with properties:
        Name: "tipper"
        AndMethod: "min"
        OrMethod: "max"
```

```
ImplicationMethod: "min"  
AggregationMethod: "max"  
DefuzzificationMethod: "centroid"  
    Inputs: [1x2 fisvar]  
    Outputs: [1x1 fisvar]  
    Rules: [1x3 fisrule]  
DisableStructuralChecks: 0
```

See 'getTunableSettings' method for parameter optimization.

Input Arguments

fisOld — Old-format fuzzy inference system

structure | matrix

Old-format fuzzy inference system, specified as a structure or a matrix.

Output Arguments

fisNew — New-format fuzzy inference system

mamfis object | sugfis object

New-format fuzzy inference system, returned as a mamfis object or a sugfis object.

See Also

mamfis | sugfis

Introduced in R2018b

convertToStruct

Convert fuzzy inference system object into a structure

Syntax

```
fisStructure = convertToStruct(fisObject)
```

Description

`fisStructure = convertToStruct(fisObject)` converts a fuzzy inference system object into a structure.

Examples

Convert FIS Object into Structure

Load a fuzzy inference system.

```
fisObject = readfis('tipper')

fisObject =
    mamfis with properties:

        Name: "tipper"
        AndMethod: "min"
        OrMethod: "max"
        ImplicationMethod: "min"
        AggregationMethod: "max"
        DefuzzificationMethod: "centroid"
        Inputs: [1x2 fisvar]
        Outputs: [1x1 fisvar]
        Rules: [1x3 fisrule]
    DisableStructuralChecks: 0
```

See 'getTunableSettings' method for parameter optimization.

Convert the fuzzy inference system object into a structure.

```
fisStructure = convertToStruct(fisObject)
```

```
fisStructure = struct with fields:
    name: 'tipper'
    type: 'mamdani'
    andMethod: 'min'
    orMethod: 'max'
    defuzzMethod: 'centroid'
    impMethod: 'min'
    aggMethod: 'max'
    input: [1x2 struct]
    output: [1x1 struct]
```

rule: [1x3 struct]

Input Arguments

fisObject – Fuzzy inference system object

mamfis object | sugfis object

Fuzzy inference system object, specified as a mamfis or sugfis object.

Output Arguments

fisStructure – Fuzzy inference system structure

structure

Fuzzy inference system structure, returned as a structure. The fields of the structure correspond to the properties of the FIS object. For object properties that are themselves objects, the corresponding structure field is a structure.

See Also

mamfis | sugfis

Topics

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced in R2018b

convertToSugeno

Convert Mamdani fuzzy inference system into Sugeno fuzzy inference system

Syntax

```
sugenoFIS = convertToSugeno(mamdaniFIS)
```

Description

`sugenoFIS = convertToSugeno(mamdaniFIS)` converts the Mamdani fuzzy inference system `mamdaniFIS` into a Sugeno fuzzy inference system `sugenoFIS`.

Examples

Transform Mamdani FIS into Sugeno FIS

Load a Mamdani fuzzy inference system.


```
mam_fis = readfis('mam22.fis');
```

Convert this system to a Sugeno fuzzy inference system.

```
sug_fis = convertToSugeno(mam_fis);
```

Plot the output surfaces for both fuzzy systems.

```
subplot(2,2,1)
gensurf(mam_fis)
title('Mamdani system (Output 1)')
subplot(2,2,2)
gensurf(sug_fis)
title('Sugeno system (Output 1)')
subplot(2,2,3)
gensurf(mam_fis,gensurfOptions('OutputIndex',2))
title('Mamdani system (Output 2)')
subplot(2,2,4)
gensurf(sug_fis,gensurfOptions('OutputIndex',2))
title('Sugeno system (Output 2)')
```

The output surfaces for both systems are similar.

Input Arguments

mamdaniFIS — Mamdani fuzzy inference system

mamfis object | mamfistype2 object

Mamdani fuzzy inference system, specified as a `mamfis` or `mamfistype2` object.

Output Arguments

sugenoFIS — Sugeno fuzzy inference system

sugfis object | sugfistype2 object

Sugeno fuzzy inference system, returned as one of the following:

- `sugfis` object when `mamdaniFIS` is a `mamfis` object
- `sugfistype2` object when `mamdaniFIS` is a `mamfistype2` object

`sugenoFIS`:

- Has constant output membership functions, whose values correspond to the centroids of the output membership functions in `mamdaniFIS`

- Uses the weighted-average defuzzification method
- Uses the product implication method
- Uses the sum aggregation method

The remaining properties of `sugenoFIS`, including the input membership functions and rule definitions remain unchanged from `mamdaniFIS`.

Tips

- If you have a functioning Mamdani fuzzy inference system, consider using `convertToSugeno` to convert to a more computationally efficient Sugeno structure to improve performance.

See Also

Functions

`mamfis` | `sugfis` | `mamfistype2` | `sugfistype2`

Apps

Fuzzy Logic Designer

Topics

“Mamdani and Sugeno Fuzzy Inference Systems” on page 2-2

Introduced in R2018b

convertToType1

Convert type-2 fuzzy inference system into type-1 fuzzy inference system

Syntax

```
fisT1 = convertToType1(fisT2)
```

Description

`fisT1 = convertToType1(fisT2)` converts the type-2 fuzzy inference system `fisT2` into a type-1 fuzzy inference system `fisT1`.

Examples


Convert Type-2 FIS to Type-1 FIS

Create a type-2 fuzzy inference system. For this example, Create a type-2 Mamdani FIS with two inputs, one output.

```
fisT2 = mamfistype2("NumInputs",2,"NumOutputs",1);
```

View the membership function for the first input variable.

```
plotmf(fisT2,"input",1)
```




Convert `fisT2` into a type-1 fuzzy inference system.

```
fisT1 = convertToType1(fisT2);
```

View the converted membership functions for the first input variable.

```
plotmf(fisT1,"input",1)
```



Input Arguments

fisT2 — Type-2 fuzzy inference system

mamfistype2 object | sugfistype2 object

Type-2 fuzzy inference system, specified as a mamfistype2 or sugfistype2 object.

Output Arguments

fisT1 — Type-1 fuzzy inference system

mamfis object | sugfis object

Type-1 fuzzy inference system, returned as one of the following:

- mamfis object when fisT2 is a mamfistype2 object
- sugfis object when fisT2 is a sugfistype2 object

The properties of fisT1 match the corresponding properties of fisT2, except that each type-2 membership function is converted to a type-1 membership function. The parameters of each type-1 membership function in fisT1 match the upper membership function parameters of the corresponding type-2 membership function in fisT2.

See Also

convertToType2 | convertToSugeno

Topics

“Mamdani and Sugeno Fuzzy Inference Systems” on page 2-2

“Type-2 Fuzzy Inference Systems” on page 2-7

Introduced in R2019b

convertToType2

Convert type-1 fuzzy inference system into type-2 fuzzy inference system

Syntax

```
fisT2 = convertToType2(fisT1)
```

Description

`fisT2 = convertToType2(fisT1)` converts the type-1 fuzzy inference system `fisT1` into a type-2 fuzzy inference system `fisT2`.

Examples


Convert Type-1 FIS to Type-2 FIS

Create a type-1 fuzzy inference system. For this example, load the `tipper.fis` file.

```
fisT1 = readfis('tipper');
```

View the membership function for the first input variable.

```
plotmf(fisT1,"input",1)
```




Convert `fisT1` into a type-2 fuzzy inference system.

```
fisT2 = convertToType2(fisT1);
```

View the converted membership functions for the first input variable.

```
plotmf(fisT2,"input",1)
```

Create Type-2 Fuzzy Inference System from Data

To create a type-2 FIS from input/output data, you must first create a type-1 FIS using `genfis`.

Load training data and generate a FIS using subtractive clustering.

```
load clusterDemo.dat
inputData = clusterDemo(:,1:2);
outputData = clusterDemo(:,3);
opt = genfisOptions('SubtractiveClustering',...
    'ClusterInfluenceRange',[0.5 0.25 0.3]);
fisT1 = genfis(inputData,outputData,opt);
fisT1.Outputs
```

```
ans =
    fisvar with properties:
        Name: "out1"
        Range: [-0.1274 1.1458]
        MembershipFunctions: [1x3 fsmf]
```

Convert the generated FIS to a type-2 FIS.

```
fisT2 = convertToType2(fisT1);
```

Since the initial type-1 FIS is a Sugeno system, only the input MFs are converted to type-2 MFs.

Input Arguments

fisT1 — Type-1 fuzzy inference system

`mamfis` object | `sugfis` object

Type-1 fuzzy inference system, specified as a `mamfis` or `sugfis` object.

Output Arguments

fisT2 — Type-2 fuzzy inference system

`mamfistype2` object | `sugfistype2` object

Type-2 fuzzy inference system, returned as one of the following:

- `mamfistype2` object when `fisT1` is a `mamfis` object
- `sugfistype2` object when `fisT1` is a `sugfis` object

The properties of `fisT2` match the corresponding properties of `fisT1`, except that each type-1 membership function (except for Sugeno output membership functions) is converted to a type-2 membership function. The upper membership function parameters of each type-2 membership function in `fisT2` match the membership function parameters of the corresponding type-1 membership function in `fisT1`.

`fisT2` has default `LowerScale` and `LowerLag` values and uses the default "karnikmendel" type reduction method.

See Also

`convertToType1` | `convertToSugeno`

Topics

"Mamdani and Sugeno Fuzzy Inference Systems" on page 2-2

"Type-2 Fuzzy Inference Systems" on page 2-7

Introduced in R2019b

defuzz

Defuzzify membership function

Syntax

```
output = defuzz(x,mf,method)
```

Description

`output = defuzz(x,mf,method)` returns the defuzzified output value for membership function `mf` at the variable values in `x` using the specified defuzzification method.

Examples

Obtain Defuzzified Value

```
x = -10:0.1:10;  
mf = trapmf(x,[-10 -8 -4 7]);  
out = defuzz(x,mf,'centroid')
```

```
out = -3.2857
```

Input Arguments

x — Variable values

vector

Variable values,

mf — Membership function values

vector

Membership function values, specified as a vector with the same length as `x`. Each element of `mf` contains a fuzzy membership value for the corresponding variable value in `x`.

method — Defuzzification method

'centroid' | 'bisector' | 'mom' | 'lom' | 'som' | character vector | string

Defuzzification method, specified as one of the following:

- 'centroid' — Centroid of the area under the output fuzzy set
- 'bisector' — Bisector of the area under the output fuzzy set
- 'mom' — Mean of the values for which the output fuzzy set is maximum
- 'lom' — Largest value for which the output fuzzy set is maximum
- 'som' — Smallest value for which the output fuzzy set is maximum
- Character vector or string that contains the name of a custom function in the current working folder or on the MATLAB path

For more information on:

- The built-in defuzzification methods, see “Defuzzification Methods” on page 1-25.
- Custom defuzzification methods, see “Build Fuzzy Systems Using Custom Functions” on page 2-40

Output Arguments

output — Defuzzified output value

scalar

Defuzzified output value, returned as a scalar.

See Also

Fuzzy Logic Designer

Topics

“Foundations of Fuzzy Logic” on page 1-7

“Fuzzy Inference Process” on page 1-19

“Defuzzification Methods” on page 1-25

Introduced before R2006a

dsigmf

Difference between two sigmoidal membership functions

Syntax

```
y = dsigmf(x,params)
```

Description

This function computes fuzzy membership values using the difference between two sigmoidal membership functions. You can also compute this membership function using a `fismf` object. For more information, see “`fismf` Object” on page 8-59.

This membership function is related to the `sigmf` and `psigmf` membership functions.

`y = dsigmf(x,params)` returns fuzzy membership values computed using the difference between two sigmoidal membership functions. Each sigmoidal function is given by:

$$f(x; a_k, c_k) = \frac{1}{1 + e^{-a_k(x - c_k)}}$$

To define the membership function parameters, specify `params` as the vector $[a_1 \ c_1 \ a_2 \ c_2]$.

Membership values are computed for each input value in `x`.

Examples

Obtain Difference of Two Sigmoidal Functions

Specify input values across the universe of discourse.


```
x = 0:0.1:10;
```

Evaluate membership function for the input values.

```
y = dsigmf(x,[5 2 5 7]);
```

Plot the membership function.

```
plot(x,y)
title('dsigmf, P = [5 2 5 7]')
xlabel('x')
ylabel('Degree of Membership')
ylim([-0.05 1.05])
```



Input Arguments

x — Input values

scalar | vector

Input values for which to compute membership values, specified as a scalar or vector.

params — Membership function parameters

vector of length four

Membership function parameters, specified as the vector $[a_1 \ c_1 \ a_2 \ c_2]$. Here, a_1 and c_1 are the parameters of the first sigmoidal function, and a_2 and c_2 are the parameters of the second sigmoidal function.

For each sigmoidal function, to open the function to the left or right, specify a negative or positive value for a , respectively. The magnitude of a defines the width of the transition area, and parameter c defines the center of the transition area.

To define a unimodal membership function with a maximum value of 1, specify the same signs for a_1 and a_2 , and select c values far enough apart to allow for both transition areas to reach 1.

Output Arguments

y — Membership value

scalar | vector

Membership value returned as a scalar or a vector. The dimensions of **y** match the dimensions of **x**. Each element of **y** is the membership value computed for the corresponding element of **x**.

Alternative Functionality

fismf Object

You can create and evaluate a **fismf** object that implements the **dsigmf** membership function.

```
mf = fismf("dsigmf",P);  
Y = evalmf(mf,X);
```

Here, **X**, **P**, and **Y** correspond to the **x**, **params**, and **y** arguments of **dsigmf**, respectively.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using MATLAB® Coder™.

See Also

[fismf](#) | [fismftype2](#) | [psigmf](#) | [sigmf](#) | [gaussmf](#) | [gauss2mf](#) | [gbellmf](#) | [trimf](#) | [trapmf](#) | [linsmf](#) | [linzmf](#) | [pimf](#) | [smf](#) | [zmf](#)

Topics

“Membership Functions” on page 1-9

Introduced before R2006a

evalfis

Evaluate fuzzy inference system

Syntax

```
output = evalfis(fis,input)
output = evalfis(fis,input,options)
[output,fuzzifiedIn,ruleOut,aggregatedOut,ruleFiring] = evalfis( __ )
```

Description

`output = evalfis(fis,input)` evaluates the fuzzy inference system `fis` for the input values in `input` and returns the resulting output values in `output`.

`output = evalfis(fis,input,options)` evaluates the fuzzy inference system using specified evaluation options.

`[output,fuzzifiedIn,ruleOut,aggregatedOut,ruleFiring] = evalfis(__)` returns intermediate results from the fuzzy inference process. This syntax is not supported when `fis` is a `fistree` object.

Examples

Evaluate Fuzzy Inference System

Load FIS.

```
fis = readfis('tipper');
```

Evaluate the FIS when the first input is 2 and the second input is 1.

```
output = evalfis(fis,[2 1])
```

```
output = 7.0169
```

Evaluate FIS for Multiple Input Combinations

Load FIS.

```
fis = readfis('tipper');
```

Specify the input combinations to evaluate using an array with one row per input combination.

```
input = [2 1;
         4 5;
         7 8];
```

Evaluate the FIS for the specified input combinations.


```
output = evalfis(fis,input)
```

```
output = 3×1
```

```
    7.0169
   14.4585
   20.3414
```

Each row of output is the defuzzified output value for the corresponding row of input.

Specify Number of Output Samples for FIS Evaluation

Load FIS.

```
fis = readfis('tipper');
```

Create an evalfisOptions option set, specifying the number of samples in the output fuzzy sets.

```
options = evalfisOptions('NumSamplePoints',50);
```

Evaluate the FIS using this option set.

```
output = evalfis(fis,[2 1],options);
```

Evaluate Tree of Fuzzy Inference Systems

Create a pair of Mamdani fuzzy inference systems.

```
fis1 = mamfis('Name','fis1','NumInputs',2,'NumOutputs',1);
fis2 = mamfis('Name','fis2','NumInputs',2,'NumOutputs',1);
```

Define the connection between the two.

```
con = ["fis1/output1" "fis2/input1"];
```

Create a tree of fuzzy inference systems.

```
tree = fistree([fis1 fis2],con);
```

Create an evalfisOptions option set, specifying the number of samples in the output fuzzy sets.

```
options = evalfisOptions('NumSamplePoints',50);
```

Evaluate the fistree object using a specified input combination and this option set.

```
y = evalfis(tree,[0.5 0.2 0.7],options)
```

```
y = 0.1553
```

Obtain Intermediate Fuzzy Inference Results

Load FIS.


```
fis = readfis('tipper');
```

Evaluate the FIS, and return the intermediate inference results.

```
[output, fuzzifiedIn, ruleOut, aggregatedOut, ruleFiring] = evalfis(fis, [2 1]);
```

You can examine the intermediate results to understand or visualize the fuzzy inference process. For example, view the aggregated output fuzzy set, which is the fuzzy set that `evalfis` defuzzifies to find the output value. Also, plot the defuzzified output value.

```
outputRange = linspace(fis.output.range(1), fis.output.range(2), length(aggregatedOut));
plot(outputRange, aggregatedOut, [output output], [0 1])
xlabel('Tip')
ylabel('Output Membership')
legend('Aggregated output fuzzy set', 'Defuzzified output')
```



The length of `aggregatedOutput` corresponds to the number of sample points used to discretize output fuzzy sets.

Evaluate Type-2 Fuzzy Inference System

Create a type-2 Mamdani fuzzy inference system.

```
fis = mamfistype2('NumInputs',2,'NumOutputs',1);
```

Evaluate the FIS when the first input is 0.4 and the second input is 0.72.

```
output = evalfis(fis,[0.4 0.72])
```

```
output = 0.1509
```

The output of a type-2 FIS is a crisp value.

When you obtain intermediate fuzzy inference results for a type-2 FIS, you obtain intermediate results generated using both upper and lower MF values. For example, obtain the intermediate fuzzified input values.

```
[output,fuzzifiedInput] = evalfis(fis,[0.5 0.75]);
```

View the fuzzified input values.

```
fuzzifiedInput
```

```
fuzzifiedInput = 9×4
```

```

    0         0         0         0
  1.0000     0     1.0000     0
    0         0         0         0
    0     0.4000         0     0.2500
  1.0000     0.4000     1.0000     0.2500
    0     0.4000         0     0.2500
    0     0.4000         0     0.2500
  1.0000     0.4000     1.0000     0.2500
    0     0.4000         0     0.2500
```

The first two columns contain the fuzzified values of the first and second inputs based on the upper MF for each input. The second two columns contain the fuzzified values for based on the lower MF for each input.

Input Arguments

fis — Fuzzy inference system

mamfis object | sugfis object | mamfistype2 object | sugfistype2 object | fistree object

Fuzzy inference system to be evaluated, specified as one of the following:

- **mamfis** object — Mamdani fuzzy inference system
- **sugfis** object — Sugeno fuzzy inference system
- **mamfistype2** object — Type-2 Mamdani fuzzy inference system
- **sugfistype2** object — Type-2 Sugeno fuzzy inference system
- **fistree** object - Tree of interconnected fuzzy inference systems

- Homogeneous structure created using `getFISCodeGenerationData`. For an example, see “Generate Code for Fuzzy System Using MATLAB Coder” on page 6-10.

input — Input values

M -by- N_U array

Input values, specified as an M -by- N_U array, where N_U is the number of input variables in `fis` and M is the number of input combinations to evaluate.

`evalfis` supports double-precision or single-precision input values.

options — Evaluation options

`evalfisOptions` object

Evaluation options, specified as an `evalfisOptions` object.

Output Arguments

output — Output values

array

Output values, returned as an M -by- N_Y array, where N_Y is the number of output variables in `fis`. `evalfis` evaluates `fis` for each row of input and returns the resulting defuzzified outputs in the corresponding row of output.

fuzzifiedIn — Fuzzified input values

array

Fuzzified input values, returned as an array.

When `fis` is a type-1 fuzzy inference system, `fuzzifiedIn` is an N_R -by- N_U array, where N_R is the number of rules in `fis`. Element (i,j) of `fuzzifiedIn` is the value of the input membership function for the j th input in the i th rule.

When `fis` is a type-2 fuzzy inference system, `fuzzifiedIn` is an N_R -by- $(2*N_U)$ array. The first N_U columns contain the fuzzified values of the upper membership function for each rule, and the last N_U columns contain the fuzzified values from the lower membership functions.

If `input` specifies multiple input combinations, then `fuzzifiedIn` corresponds to the combination in the last row of `input`.

For more information on fuzzifying input values, see “Fuzzify Inputs” on page 1-20.

This output argument is not supported when `fis` is a `fistree` object.

ruleOut — Rule outputs

array

Rule outputs, returned as an array. To obtain the output for each rule, `evalfis` applies the firing strength from the rule antecedent to the output membership function using the implication method specified in `fis`.

When `fis` is a type-1 Mamdani system, `ruleOut` is an N_S -by- $(N_R N_Y)$ array, where N_R is the number of rules, N_Y is the number of outputs, and N_S is the number of sample points used for evaluating output

variable ranges. Each column of `ruleOut` contains the output fuzzy set for one rule. The first N_R columns contain the rule outputs for the first output variable, the next N_R columns correspond to the second output variable, and so on.

When `fis` is a type-2 Mamdani system, `ruleOut` is an N_S -by- $(2*N_R*N_Y)$ array. The first N_R*N_Y columns contain the rule outputs generated using upper membership functions, and the last N_R*N_Y columns contain the rule outputs generated using lower membership functions.

When `fis` is a type-1 Sugeno system, each rule output is a scalar value. In this case, `ruleOut` is an N_R -by- N_Y array. Element (j,k) of `ruleOut` is the value of the k th output variable for the j th rule.

When `fis` is a type-2 Sugeno system, `ruleOut` is an N_R -by- $(3*N_Y)$ array. The first N_Y columns contain the rule output levels. The next N_Y columns contain the corresponding rule firing strengths generated using upper membership functions. The last N_Y columns contain the rule firing strengths generated using lower membership functions. For example, in a three-output system, columns 4 and 7 contain the firing strengths for the output levels in column 1.

If `input` specifies multiple input combinations, then `ruleOut` corresponds to the combination in the last row of `input`.

For more information on fuzzy implication, see “Apply Implication Method” on page 1-21.

This output argument is not supported when `fis` is a `fistree` object.

aggregatedOut — Aggregated output

array | row vector

Aggregated output for each output variable, returned as an array.

N_S -by- N_Y array or a row vector of length N_Y . For each output variable, `evalfis` combines the corresponding outputs from all the rules using the aggregation method specified in `fis`.

For a type-1 Mamdani system, the aggregate result for each output variable is a fuzzy set. In this case, `aggregatedOut` is as an N_S -by- N_Y array, where N_Y is the number of outputs and N_S is the number of sample points used for evaluating output variable ranges. Each column of `aggregatedOut` contains the aggregate fuzzy set for one output variable.

For a type-2 Mamdani system, the aggregate result for each output variable is a fuzzy set. In this case, `aggregatedOut` is as an N_S -by- $(2*N_Y)$ array. The first N_Y columns contain the aggregated outputs generated using upper membership functions, and the last N_Y columns contain the aggregated outputs generated using lower membership functions.

When `fis` is a type-1 Sugeno system, the aggregate result for each output variable is a scalar value. In this case, `aggregatedOut` is a row vector of length N_Y , where element k is the sum of the rule outputs for the k th output variable.

When `fis` is a type-2 Sugeno system, `aggregatedOut` is an N_R -by- $(3*N_Y)$ array. `aggregatedOut` contains the same data as `ruleOut` with the columns sorted based on the output levels. For example, in a three-output system, when the output levels in column 1 are sorted, the corresponding firing strengths in columns 4 and 7 are adjusted accordingly.

If `input` specifies multiple input combinations, then `aggregatedOut` corresponds to the combination in the last row of `input`.

For more information on fuzzy aggregation, see “Aggregate All Outputs” on page 1-22.

This output argument is not supported when `fis` is a `fistree` object.

ruleFiring — Rule firing strengths

column vector | array

Rule firing strength, returned as a column vector or array. To obtain the firing strength for each rule, `evalfis` evaluates the rule antecedents; that is, it applies fuzzy operator to the values of the fuzzified inputs.

For a type-1 fuzzy system, `ruleFiring` is a column vector of length N_R , where N_R is the number of rules, and element i is the firing strength of the i th rule.

For a type-2 fuzzy system, `ruleFiring` is an N_R -by-2 array. The first column contains the rule firing strengths generated using upper membership functions, and the second column contains the rule firing strengths generated using lower membership functions.

If `input` specifies multiple input combinations, then `ruleFiring` corresponds to the combination in the last row of `input`.

For more information on applying the fuzzy operator, see “Apply Fuzzy Operator” on page 1-20.

This output argument is not supported when `fis` is a `fistree` object.

Alternative Functionality

App

You can evaluate type-1 fuzzy inference systems using the **Rule Viewer** in the **Fuzzy Logic Designer** app.

Simulink Block

You can evaluate fuzzy inference systems using the Fuzzy Logic Controller block. For more information on mapping the arguments of `evalfis` to the Fuzzy Logic Controller block, see “Simulate Fuzzy Inference Systems in Simulink” on page 5-2.

Compatibility Considerations

evalfis input argument order has changed

Behavior changed in R2018b

The order of input arguments for `evalfis` has changed, which requires updates to your code.

Update Code

Previously, to evaluate a fuzzy inference system, `fis`, you specified the input variable values, `input`, as the first input argument. For example:

```
output = evalfis(input,fis);  
output = evalfis(input,fis,options);
```

Update your code to specify the fuzzy inference system as the first input argument. For example:

```
output = evalfis(fis,input);  
output = evalfis(fis,input,options);
```

To specify the number of sample points for output fuzzy sets, you now use an `evalfisOptions` object

Behavior changed in R2018a

To specify the number of sample points for output fuzzy sets, you now use an `evalfisOptions` object, which requires updates to your code.

Update Code

Previously, to specify the number of sample points, `numPts`, to use when evaluating output fuzzy sets of fuzzy inference system `fis`, you used an input argument. For example:

```
output = evalfis(input,fis,numPts);
```

Update your code to specify the number of sample points using an `evalfisOptions` object. For example:

```
opt = evalfisOptions('NumSamplePoints',numPts);
output = evalfis(input,fis,opt);
```

`evalfis` diagnostic message behavior has changed

Behavior changed in R2018a

The diagnostic message behavior of the `evalfis` function has changed. Previously, the `evalfis` function had the following behaviors for diagnostic conditions.

Diagnostic Condition	Previous Behavior
Input values outside of their specified variable ranges	MATLAB warning
No rules fired for a given output at the current input values	MATLAB Command Window message
Empty output fuzzy sets	MATLAB Command Window message

Starting in R2018a, these diagnostic conditions are reported as MATLAB warnings by default. You can change this behavior by specifying the corresponding options in an `evalfisOptions` object.

Update Code

To disable the default warning messages, update your code to use an `evalfisOptions` object, and specify the diagnostic message options. For example, disable the empty output fuzzy set message.

```
opt = evalfisOptions('EmptyOutputFuzzySetMessage','none');
output = evalfis(input,fis,opt);
```

Intermediate fuzzy inference outputs for Sugeno systems are now analogous to outputs for Mamdani systems

Behavior changed in R2018a

When evaluating a Sugeno system using the following syntax, the intermediate fuzzy inference results are now analogous to the intermediate results for Mamdani systems.

```
[output,fuzzifiedInputs,ruleOutputs,aggregatedOutput] = evalfis(input,fis);
```

For a Sugeno system:

- `ruleOutputs` now returns an array that contains the scalar output value for each rule; that is, the product of the rule firing strength and the rule output level.
- `aggregatedOutput` now returns the sum of all the rule output values for each output variable.

Previously, for a Sugeno fuzzy system:

- `ruleOutputs` returned an array that contained the output level for each rule.
- `aggregatedOutput` returned an array that contained the firing strength for each rule.

Starting in R2018a, if your code returns intermediate fuzzy inference results when evaluating a Sugeno system using `evalfis`, modify your code to use the new `ruleOutputs` and `aggregatedOutput` results.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using MATLAB® Coder™.

Usage notes and limitations:

- All `evalfis` syntaxes are supported for code generation. However, `mamfis`, `sugfis`, and `fistree` objects are not supported. To use `evalfis` for code generation, you must convert your FIS objects into homogeneous structures using `getFISCodeGenerationData`.
- Unlike the Fuzzy Logic Controller block, `evalfis` does not support fixed-point data for simulation or code generation.
- When evaluating a fuzzy inference system in Simulink, it is recommended to not use `evalfis` or `evalfisOptions` within a MATLAB Function block. Instead, evaluate your fuzzy inference system using a Fuzzy Logic Controller block.

See Also

Functions

`mamfis` | `sugfis` | `evalfisOptions` | `fistree`

Topics

“Fuzzy Inference Process” on page 1-19

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced before R2006a

evalmf

Evaluate fuzzy membership function

Syntax

```
y = evalmf(mfT1,x)
```

```
[yUpper,yLower] = evalmf(mfT2,x)
```

Description

`y = evalmf(mfT1,x)` evaluates one or more type-1 membership functions based on the input values in `x`, returning the membership function values.

`[yUpper,yLower] = evalmf(mfT2,x)` evaluates one or more type-2 membership function based on the input values in `x`, returning both the upper and lower membership function values.

Examples


Evaluate Membership Function

Evaluate a generalized bell-shaped membership function across a range of input values from 0 through 10.

```
x = 0:0.1:10;  
mf = fismf("gbellmf",[2 4 6]);  
y = evalmf(mf,x);
```

Plot the evaluation.

```
plot(x,y)  
xlabel('gbellmf, P = [2 4 6]')
```



Evaluate Multiple Membership Functions

Create a vector of three Gaussian membership functions.

```
mf = [fismf("gaussmf",[0.9 2.5],'Name',"low");  
      fismf("gaussmf",[0.9 5],'Name',"medium");  
      fismf("gaussmf",[0.9 7.55],'Name',"high")];
```

Specify the input range over which to evaluate the membership functions.


```
x = (-2:0.1:12)';
```

Evaluate the membership functions.

```
y = evalmf(mf,x);
```

Plot the evaluation results.

```
plot(x,y)  
xlabel('Input (x)')  
ylabel('Membership value (y)')  
legend("low","medium","high")
```



Evaluate Type-2 Membership Function

Create a triangular type-2 membership function.


```
mf = fismftype2("trimf",[5 7 9], 'LowerLag',0.3, 'LowerScale',0.8);
```

Evaluate the membership function across a range of input values from 0 through 10.

```
x = 0:0.1:10;
[yUpper,yLower] = evalmf(mf,x);
```

Plot the evaluated upper and lower MFs.

```
plot(x,yUpper,x,yLower)
legend('Upper MF', 'Lower MF', 'Location', 'northwest')
xlabel('Input')
ylabel('Membership value')
```



Input Arguments

mfT1 — Type-1 membership function

fismf object | vector of fismf objects

Type-1 membership function, specified as a fismf object or a vector of such objects.

x — Input value

scalar | vector | 2-D matrix

Input value, specified as a scalar, vector, or 2-D matrix. If mf is a:

- Single fismf object, then you can specify x as a scalar, vector, or matrix
- Vector of fismf objects, then you can specify x as a scalar or vector

mfT2 — Type-2 membership function

fismftype2 object | array of fismftype2 objects

Type-2 membership function, specified as a fismftype2 object or a vector of such objects.

Output Arguments

y — Membership values for a type-1 membership function

scalar | vector | 2-D matrix

Membership value for a type-1 membership function, returned as a scalar, vector, or 2-D matrix. If `mfT1` is a:

- Single `fismf` object, then `y` is a scalar, vector, or matrix with the same dimensions as `x`. Each element of `y` is the evaluated membership value for the corresponding element of `x`.
- Vector of `fismf` objects, then `y` is an M -by- N matrix, where M and N are the lengths of `mfT1` and `x`, respectively. `y(i,j)` is the evaluated value of membership function `mfT1(i)` for input value `x(j)`.

yUpper — Upper MF membership values for a type-2 membership function

scalar | vector | 2-D matrix

Upper MF membership value for a type-2 membership function, returned as a scalar, vector, or 2-D matrix. If `mfT2` is a:

- Single `fismftype2` object, then `y` is a scalar, vector, or matrix with the same dimensions as `x`. Each element of `y` is the evaluated membership value for the corresponding element of `x`.
- Vector of `fismftype2` objects, then `y` is an M -by- N matrix, where M and N are the lengths of `mfT2` and `x`, respectively. `y(i,j)` is the evaluated value of membership function `mfT2(i)` for input value `x(j)`.

yLower — Lower MF membership values for a type-2 membership function

scalar | vector | 2-D matrix

Lower MF membership value for a type-2 membership function, returned as a scalar, vector, or 2-D matrix. If `mfT2` is a:

- Single `fismftype2` object, then `y` is a scalar, vector, or matrix with the same dimensions as `x`. Each element of `y` is the evaluated membership value for the corresponding element of `x`.
- Vector of `fismftype2` objects, then `y` is an M -by- N matrix, where M and N are the lengths of `mfT2` and `x`, respectively. `y(i,j)` is the evaluated value of membership function `mfT2(i)` for input value `x(j)`.

Compatibility Considerations

evalmf now takes a fismf object as an input argument

Behavior changed in R2018b

`evalmf` now takes a `fismf` object as an input argument rather than the type and parameters of the membership function. Also, you can now evaluate multiple membership functions by passing an array of `fismf` objects to `evalmf`. There are differences between these approaches that require updates to your code.

Update Code

Previously, you evaluated a membership function for given input values, `x`, by specifying the type of membership function, `type`, and the membership functions parameters, `params`.

```
y = evalmf(x,params,type);
```

Update your code to first create a `fismf` object, `mf`. Then, pass this object to `evalmf`.

```
mf = fismf(type,params);
y = evalmf(mf,x);
```

Also, previously, to evaluate multiple membership functions you called `evalmf` once for each membership function.

```
y1 = evalmf(x,params1,type1);  
y2 = evalmf(x,params2,type2);  
y3 = evalmf(x,params3,type3);
```

Now, you can evaluate multiple membership functions by passing an array of `fismf` objects to `evalmf`.

```
mf1 = fismf(type1,params1);  
mf2 = fismf(type2,params2);  
mf3 = fismf(type3,params3);  
y = evalmf([mf1 mf2 mf3],x);
```

Here, `y = [y1 y2 y3]'`;

See Also

`fismf` | `fismftype2`

Topics

“Foundations of Fuzzy Logic” on page 1-7

Introduced before R2006a

fcm

Fuzzy c-means clustering

Syntax

```
[centers,U] = fcm(data,Nc)
[centers,U] = fcm(data,Nc,options)

[centers,U,objFunc] = fcm( ___ )
```

Description

`[centers,U] = fcm(data,Nc)` performs fuzzy c-means clustering on the given data and returns `Nc` cluster centers.

`[centers,U] = fcm(data,Nc,options)` specifies additional clustering options.

`[centers,U,objFunc] = fcm(___)` also returns the objective function values at each optimization iteration for all of the previous syntaxes.

Examples

Cluster Data Using Fuzzy C-Means Clustering

Load data.

```
load fcmdata.dat
```

Find 2 clusters using fuzzy c-means clustering.

```
[centers,U] = fcm(fcmdata,2);

Iteration count = 1, obj. fcn = 8.970479
Iteration count = 2, obj. fcn = 7.197402
Iteration count = 3, obj. fcn = 6.325579
Iteration count = 4, obj. fcn = 4.586142
Iteration count = 5, obj. fcn = 3.893114
Iteration count = 6, obj. fcn = 3.810804
Iteration count = 7, obj. fcn = 3.799801
Iteration count = 8, obj. fcn = 3.797862
Iteration count = 9, obj. fcn = 3.797508
Iteration count = 10, obj. fcn = 3.797444
Iteration count = 11, obj. fcn = 3.797432
Iteration count = 12, obj. fcn = 3.797430
```

Classify each data point into the cluster with the largest membership value.


```
maxU = max(U);
index1 = find(U(1,:) == maxU);
index2 = find(U(2,:) == maxU);
```

Plot the clustered data and cluster centers.

```

plot(fcmdata(index1,1),fcmdata(index1,2),'ob')
hold on
plot(fcmdata(index2,1),fcmdata(index2,2),'or')
plot(centers(1,1),centers(1,2),'xb','MarkerSize',15,'LineWidth',3)
plot(centers(2,1),centers(2,2),'xr','MarkerSize',15,'LineWidth',3)
hold off

```



Specify Fuzzy Overlap Between Clusters

Create a random data set.

```
data = rand(100,2);
```

To increase the amount of fuzzy overlap between the clusters, specify a large fuzzy partition matrix exponent.

```
options = [3.0 NaN NaN 0];
```

Cluster the data.

```
[centers,U] = fcm(data,2,options);
```


Configure Clustering Termination Conditions

Load the clustering data.

```
load clusterDemo.dat
```

Set the clustering termination conditions such that the optimization stops when either of the following occurs:

- The number of iterations reaches a maximum of 25.
- The objective function improves by less than 0.001 between two consecutive iterations.

```
options = [NaN 25 0.001 0];
```

The first option is NaN, which sets the fuzzy partition matrix exponent to its default value of 2. Setting the fourth option to 0 suppresses the objective function display.

Cluster the data.

```
[centers,U,objFun] = fcm(clusterDemo,3,options);
```

To determine which termination condition stopped the clustering, view the objective function vector.

```
objFun
```

```
objFun = 13×1
```

```
54.7257
42.9867
42.8554
42.1857
39.0857
31.6814
28.5736
27.1806
20.7359
15.7147
⋮
```

The optimization stopped because the objective function improved by less than 0.001 between the final two iterations.

Input Arguments

data — Data set to be clustered

matrix

Data set to be clustered, specified as a matrix with N_d rows, where N_d is the number of data points. The number of columns in `data` is equal to the data dimensionality.

Nc — Number of clusters

integer greater than 1

Number of clusters to create, specified as an integer greater than 1.

options – Clustering options

vector

Clustering options, specified as a vector with the following elements:

Option	Description	Default
options (1)	Exponent for the fuzzy partition matrix, U , specified as a scalar greater than 1.0. This option controls the amount of fuzzy overlap between clusters, with larger values indicating a greater degree of overlap. If your data set is wide with a lot of overlap between potential clusters, then the calculated cluster centers might be very close to each other. In this case, each data point has approximately the same degree of membership in all clusters. To improve your clustering results, decrease this value, which limits the amount of fuzzy overlap during clustering. For an example of fuzzy overlap adjustment, see “Adjust Fuzzy Overlap in Fuzzy C-Means Clustering” on page 4-7.	2.0
options (2)	Maximum number of iterations, specified as a positive integer.	100
options (3)	Minimum improvement in objective function between two consecutive iterations, specified as a positive scalar.	1e-5
options (4)	Information display flag indicating whether to display the objective function value after each iteration, specified as one of the following: <ul style="list-style-type: none"> • <code>true</code> — Display objective function. • <code>false</code> — Do not display objective function. 	<code>true</code>

If any element of `options` is `NaN`, the default value for that option is used.

The clustering process stops when the maximum number of iterations is reached or when the objective function improvement between two consecutive iterations is less than the specified minimum.

Output Arguments**centers – Cluster centers**

matrix

Final cluster centers, returned as a matrix with N_c rows containing the coordinates of each cluster center. The number of columns in `centers` is equal to the dimensionality of the data being clustered.

U – Fuzzy partition matrix

matrix

Fuzzy partition matrix, returned as a matrix with N_c rows and N_d columns. Element $U(i, j)$ indicates the degree of membership of the j th data point in the i th cluster. For a given data point, the sum of the membership values for all clusters is one.

objFunc – Objective function values

vector

Objective function values for each iteration, returned as a vector.

Tips

- To generate a fuzzy inference system using FCM clustering, use the `genfis` command. For example, suppose you cluster your data using the following syntax:

```
[centers,U] = fcm(data,Nc,options);
```

where the first M columns of `data` correspond to input variables, and the remaining columns correspond to output variables.

You can generate a fuzzy system using the same training data and FCM clustering configuration. To do so:

- 1 Configure clustering options.

```
opt = genfisOptions('FCMClustering');
opt.NumClusters = Nc;
opt.Exponent = options(1);
opt.MaxNumIteration = options(2);
opt.MinImprovement = options(3);
opt.Verbose = options(4);
```

- 2 Extract the input and output variable data.

```
inputData = data(:,1:M);
outputData = data(:,M+1:end);
```

- 3 Generate the FIS structure.

```
fis = genfis(inputData,outputData,opt);
```

The fuzzy system, `fis`, contains one fuzzy rule for each cluster, and each input and output variable has one membership function per cluster. For more information, see `genfis` and `genfisOptions`.

Algorithms

Fuzzy c-means (FCM) is a clustering method that allows each data point to belong to multiple clusters with varying degrees of membership.

FCM is based on the minimization of the following objective function

$$J_m = \sum_{i=1}^D \sum_{j=1}^N \mu_{ij}^m \|x_i - c_j\|^2,$$

where

- D is the number of data points.
- N is the number of clusters.
- m is fuzzy partition matrix exponent for controlling the degree of fuzzy overlap, with $m > 1$. Fuzzy overlap refers to how fuzzy the boundaries between clusters are, that is the number of data points that have significant membership in more than one cluster.

- x_i is the i th data point.
- c_j is the center of the j th cluster.
- μ_{ij} is the degree of membership of x_i in the j th cluster. For a given data point, x_i , the sum of the membership values for all clusters is one.

fcm performs the following steps during clustering:

- 1 Randomly initialize the cluster membership values, μ_{ij} .
- 2 Calculate the cluster centers:

$$c_j = \frac{\sum_{i=1}^D \mu_{ij}^m x_i}{\sum_{i=1}^D \mu_{ij}^m}.$$

- 3 Update μ_{ij} according to the following:

$$\mu_{ij} = \frac{1}{\sum_{k=1}^N \left(\frac{\|x_i - c_j\|}{\|x_i - c_k\|} \right)^{\frac{2}{m-1}}}.$$

- 4 Calculate the objective function, J_m .
- 5 Repeat steps 2-4 until J_m improves by less than a specified minimum threshold or until after a specified maximum number of iterations.

References

- [1] Bezdek, J.C., *Pattern Recognition with Fuzzy Objective Function Algorithms*, Plenum Press, New York, 1981.

See Also

genfis | findcluster

Topics

"Fuzzy Clustering" on page 4-2

"Cluster Quasi-Random Data Using Fuzzy C-Means Clustering" on page 4-4

"Adjust Fuzzy Overlap in Fuzzy C-Means Clustering" on page 4-7

Introduced before R2006a

findcluster

Open clustering tool

Syntax

```
findcluster  
findcluster(fileName)
```

Description

`findcluster` opens a UI to implement either fuzzy c-means or fuzzy subtractive clustering. For more information on:

- Clustering methods, see “Fuzzy Clustering” on page 4-2
- Using the Clustering tool, see “Cluster Data Using Clustering Tool” on page 4-29


`findcluster(fileName)` opens the UI, loads the data set in the file specified by `fileName`, and plots the first two dimensions of the data.

Examples

Open Clustering Tool

Open the Clustering tool and load the data set in `clusterdemo.dat`.

```
findcluster('clusterDemo.dat')
```



You can configure the clustering options.

To cluster the data, click **Start**.

Input Arguments

fileName — Data file name

string | character vector

Data file name, specified as a string or character vector.

The data set file must have the extension `.dat`. Each line of the data set file contains one data point. For example, if you have 5-dimensional data with 100 data points, the file contains 100 lines, and each line contains five values.

Tips

- Using the Clustering tool, you can obtain only the computed cluster centers. To obtain additional information for:

- Fuzzy c-means clustering, such as the fuzzy partition matrix, cluster the data using `fcm`.
- Subtractive clustering, such as the range of influence in each data dimension, cluster the data using `subclust`.
- To use the same clustering data with either `fcm` or `subclust`, first load the data file into the MATLAB workspace. For example, at the MATLAB command line, type:

```
load clusterdemo.dat
```

See Also

`fcm` | `subclust`

Topics

“Fuzzy Clustering” on page 4-2

“Cluster Data Using Clustering Tool” on page 4-29

Introduced before R2006a

fuzarith

Perform fuzzy arithmetic

Syntax

```
C = fuzarith(X,A,B,operator)
```

Description

`C = fuzarith(X,A,B,operator)` returns the fuzzy set C, which is the result of applying the specified fuzzy operator to the fuzzy sets A and B. The operation is performed across the universe of discourse X

Examples

Perform Fuzzy Arithmetic

Specify Gaussian and trapezoidal membership functions.

```
N = 501;
minX = -20;
maxX = 20;
x = linspace(minX,maxX,N);
```


```
A = trapmf(x,[-10 -2 1 3]);
B = gaussmf(x,[2 5]);
```

Evaluate the sum, difference, product, and quotient of A and B.

```
Csum = fuzarith(x,A,B,'sum');
Csub = fuzarith(x,A,B,'sub');
Cprod = fuzarith(x,A,B,'prod');
Cdiv = fuzarith(x,A,B,'div');
```


Plot the addition and subtraction results.

```
figure
subplot(2,1,1)
plot(x,A,'--',x,B,':',x,Csum,'c')
title('Fuzzy Addition, A+B')
legend('A','B','A+B')
subplot(2,1,2)
plot(x,A,'--',x,B,':',x,Csub,'c')
title('Fuzzy Subtraction, A-B')
legend('A','B','A-B')
```

Plot the multiplication and division results.

```
figure
subplot(2,1,1)
plot(x,A,'--',x,B,':',x,Cprod,'c')
title('Fuzzy Multiplication, A*B')
legend('A','B','A*B')
subplot(2,1,2)
plot(x,A,'--',x,B,':',x,Cdiv,'c')
title('Fuzzy Division, A/B')
legend('A','B','A/B')
```



Input Arguments

X — Universe of discourse

vector

Universe of discourse, specified as a vector.

A — Input fuzzy set

vector

Input fuzzy set, specified as a vector with the same length as X. Each element of A is the value of the fuzzy set for the corresponding value of X.

A must be a convex fuzzy set. For more information, see “Algorithms” on page 8-87.

B — Input fuzzy set

vector

Input fuzzy set, specified as a vector with the same length as X. Each element of B is the value of the fuzzy set for the corresponding value of X.

B must be a convex fuzzy set. For more information, see “Algorithms” on page 8-87.

operator — Fuzzy arithmetic operator

'sum' | 'sub' | 'prod' | 'div'

Arithmetic operator, specified as one of the following:

- 'sum' — Fuzzy addition
- 'sub' — Fuzzy subtraction
- 'prod' — Fuzzy multiplication
- 'div' — Fuzzy division

For more information on fuzzy arithmetic operations, see “Algorithms” on page 8-87.

Note Fuzzy addition can generate the message "divide by zero". However, this warning does not affect the accuracy of `fuzarith`.

Output Arguments

C — Output fuzzy set

column vector

Output fuzzy set, returned as a column vector with length equal to the length of X.

Algorithms

To perform fuzzy arithmetic operations, the fuzzy operands (input fuzzy sets A and B) must be convex fuzzy sets. A fuzzy set is convex if, for each pair of points x_1 and x_2 in the universe of discourse X and $\lambda \in [0,1]$,

$$\mu(\lambda x_1 + (1 - \lambda)x_2) \geq \min(\mu(x_1), \mu(x_2))$$

An α -cut of a fuzzy set is the region in the universe of discourse for which the fuzzy set has a specific membership value, α . For a convex fuzzy set, every α -cut defines a continuous region in the universe of discourse.

`fuzarith` uses the continuous regions defined by the α -cuts of fuzzy sets A and B to compute the corresponding α -cut of the output fuzzy set C. To do so, `fuzarith` uses interval arithmetic.

The following table shows how to compute the left and right boundaries of the output interval. Here:

- $[A_L A_R]$ is the interval defined by the α -cut of fuzzy set A.
- $[B_L B_R]$ is the interval defined by the α -cut of fuzzy set B.
- $[C_L C_R]$ is the interval defined by the α -cut of fuzzy set C.

Interval Arithmetic Operator	Definition
Addition: $C = A+B$	$C_L = A_L + B_L$ $C_R = A_R + B_R$
Subtraction: $C = A-B$	$C_L = A_L - B_R$ $C_R = A_R - B_L$
Multiplication: $C = A*B$	$C_L = \min(A_L \cdot B_L, A_L \cdot B_R, A_R \cdot B_L, A_R \cdot B_R)$ $C_R = \max(A_L \cdot B_L, A_L \cdot B_R, A_R \cdot B_L, A_R \cdot B_R)$

Interval Arithmetic Operator	Definition
Division: $C = A/B$	$C_L = \min\left(\frac{A_L}{B_L}, \frac{A_L}{B_R}, \frac{A_R}{B_L}, \frac{A_R}{B_R}\right)$ $C_R = \max\left(\frac{A_L}{B_L}, \frac{A_L}{B_R}, \frac{A_R}{B_L}, \frac{A_R}{B_R}\right)$

See Also

Topics

“What Is Fuzzy Logic?” on page 1-3

“Foundations of Fuzzy Logic” on page 1-7

Introduced before R2006a

gauss2mf

Gaussian combination membership function

Syntax

`y = gauss2mf(x,params)`

Description

This function computes fuzzy membership values using a combination of two Gaussian membership functions. You can also compute this membership function using a `fismf` object. For more information, see “`fismf` Object” on page 8-91.

`y = gauss2mf(x,params)` returns fuzzy membership values computed using a combination of two Gaussian membership functions computed. Each Gaussian function defines the shape of one side of the membership function and is given by:

$$f(x; \sigma, c) = e^{-\frac{(x-c)^2}{2\sigma^2}}$$

To specify the standard deviation, σ , and mean, c , for each Gaussian function, use `params`.

Membership values are computed for each input value in `x`.

Examples

Gaussian Combination Membership Functions

Specify input values across the universe of discourse.


```
x = 0:0.1:10;
```

Evaluate several membership functions for the input values.

```
y1 = gauss2mf(x,[2 4 1 8]);
y2 = gauss2mf(x,[2 5 1 7]);
y3 = gauss2mf(x,[2 6 1 6]);
```

Plot the membership function.

```
plot(x,y1,x,y2,x,y3)
xlabel('x')
ylabel('Degree of Membership')
ylim([-0.05 1.05])
legend('P = [2 4 1 8]', 'P = [2 5 1 7]', 'P = [2 6 1 6]', ...
       'Location','northwest')
```



Input Arguments

x – Input values

scalar | vector

Input values for which to compute membership values, specified as a scalar or vector.

params – Membership function parameters

vector of length four

Membership function parameters, specified as the vector $[\sigma_1 \ c_1 \ \sigma_2 \ c_2]$. Here:

- σ_1 and c_1 are the standard deviation and mean of the left Gaussian function, respectively.
- σ_2 and c_2 are the standard deviation and mean of the right Gaussian function, respectively.

When $c_1 \leq c_2$, the `gauss2mf` function reaches a maximum value of 1 over the range $[c_1, c_2]$.

Otherwise, when $c_1 > c_2$, the maximum value is less than one.

Output Arguments

y – Membership value

scalar | vector

Membership value, returned as a scalar or a vector. The dimensions of `y` match the dimensions of `x`. Each element of `y` is the membership value computed for the corresponding element of `x`.

Alternative Functionality

fismf Object

You can create and evaluate a `fismf` object that implements the `gauss2mf` membership function.

```
mf = fismf("gauss2mf",P);  
Y = evalmf(mf,X);
```

Here, `X`, `P`, and `Y` correspond to the `x`, `params`, and `y` arguments of `gauss2mf`, respectively.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using MATLAB® Coder™.

See Also

`psigmf` | `sigmf` | `gaussmf` | `gbellmf` | `trimf` | `trapmf` | `linsmf` | `linzmf` | `pimf` | `smf` | `zmf` | `dsigmf`

Topics

"Membership Functions" on page 1-9

Introduced before R2006a

gaussmf

Gaussian membership function

Syntax

```
y = gaussmf(x,params)
```

Description

This function computes fuzzy membership values using a Gaussian membership function. You can also compute this membership function using a `fismf` object. For more information, see “`fismf` Object” on page 8-94.

A Gaussian membership function is not the same as a Gaussian probability distribution. For example, a Gaussian membership function always has a maximum value of 1. For more information on Gaussian probability distributions, see “Normal Distribution” (Statistics and Machine Learning Toolbox).

`y = gaussmf(x,params)` returns fuzzy membership values computed using the following Gaussian membership function:

$$f(x; \sigma, c) = e^{-\frac{(x-c)^2}{2\sigma^2}}$$

To specify the standard deviation, σ , and mean, c , for the Gaussian function, use `params`.

Membership values are computed for each input value in `x`.

Examples

Gaussian Membership Function

Specify input values across the universe of discourse.


```
x = 0:0.1:10;
```

Evaluate membership function for the input values.

```
y = gaussmf(x,[2 5]);
```

Plot the membership function.

```
plot(x,y)
xlabel('gaussmf, P=[2 5]')
ylabel('Membership')
ylim([-0.05 1.05])
```

Input Arguments

x — Input values

scalar | vector

Input values for which to compute membership values, specified as a scalar or vector.

params — Membership function parameters

vector of length two

Membership function parameters, specified as the vector $[\sigma \ c]$, where σ is the standard deviation and c is the mean.

Output Arguments

y — Membership value

scalar | vector

Membership value returned as a scalar or a vector. The dimensions of y match the dimensions of x . Each element of y is the membership value computed for the corresponding element of x .

Alternative Functionality

fismf Object

You can create and evaluate a `fismf` object that implements the `gaussmf` membership function.

```
mf = fismf("gaussmf",P);  
Y = evalmf(mf,X);
```

Here, `X`, `P`, and `Y` correspond to the `x`, `params`, and `y` arguments of `gaussmf`, respectively.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using MATLAB® Coder™.

See Also

`psigmf` | `sigmf` | `gauss2mf` | `gbellmf` | `trimf` | `trapmf` | `linsmf` | `linzmf` | `pimf` | `smf` | `zmf` | `dsigmf`

Topics

“Membership Functions” on page 1-9

Introduced before R2006a

gbellmf

Generalized bell-shaped membership function

Syntax

```
y = gbellmf(x,params)
```

Description

This function computes fuzzy membership values using a generalized bell-shaped membership function. You can also compute this membership function using a `fismf` object. For more information, see “`fismf` Object” on page 8-97.

`y = gbellmf(x,params)` returns fuzzy membership values computed using the following generalized bell-shaped membership function:

$$f(x; a, b, c) = \frac{1}{1 + \left| \frac{x-c}{a} \right|^{2b}}$$

To configure the membership function, specify parameters, a , b , and c using `params`.

Membership values are computed for each input value in `x`.

Examples

Generalized Bell-Shaped Membership Function

Specify input values across the universe of discourse.


```
x = 0:0.1:10;
```

Evaluate membership function for the input values.

```
y = gbellmf(x,[2 4 6]);
```

Plot the membership function.

```
plot(x,y)
title('gbellmf, P=[2 4 6]')
xlabel('x')
ylabel('Degree of Membership')
ylim([-0.05 1.05])
```



Input Arguments

x — Input values

scalar | vector

Input values for which to compute membership values, specified as a scalar or vector.

params — Membership function parameters

vector of length three

Membership function parameters, specified as the vector $[a \ b \ c]$.

Here:

- a defines the width of the membership function, where a larger value creates a wider membership function.
- b defines the shape of the curve on either side of the central plateau, where a larger value creates a more steep transition.
- c defines the center of the membership function.

Output Arguments

y — Membership value

scalar | vector

Membership value returned as a scalar or a vector. The dimensions of y match the dimensions of x . Each element of y is the membership value computed for the corresponding element of x .

Alternative Functionality

fismf Object

You can create and evaluate a `fismf` object that implements the `gbellmf` membership function.

```
mf = fismf("gbellmf",P);  
Y = evalmf(mf,X);
```

Here, X , P , and Y correspond to the x , `params`, and y arguments of `gbellmf`, respectively.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using MATLAB® Coder™.

See Also

`psigmf` | `sigmf` | `gaussmf` | `gauss2mf` | `trimf` | `trapmf` | `linsmf` | `linzmf` | `pimf` | `smf` | `zmf` | `dsigmf`

Topics

"Membership Functions" on page 1-9

Introduced before R2006a

genfis

Generate fuzzy inference system object from data

Syntax

```
fis = genfis(inputData,outputData)
fis = genfis(inputData,outputData,options)
```

Description

`fis = genfis(inputData,outputData)` returns a single-output Sugeno fuzzy inference system (FIS) using a grid partition of the given input and output data.

`fis = genfis(inputData,outputData,options)` returns a FIS generated using the specified input/output data and the options specified in `options`.. You can generate fuzzy systems using grid partitioning, subtractive clustering, or fuzzy c-means (FCM) clustering.

Examples

Generate Fuzzy Inference System Using Default Options

Define training data.

```
inputData = [rand(10,1) 10*rand(10,1)-5];
outputData = rand(10,1);
```

Generate a fuzzy inference system.

```
fis = genfis(inputData,outputData);
```

The generated system, `fis`, is created using grid partitioning with default options.

Generate FIS Using Grid Partitioning

Define training data.

```
inputData = [rand(10,1) 10*rand(10,1)-5];
outputData = rand(10,1);
```

Create a default `genfisOptions` option set for grid partitioning.

```
opt = genfisOptions('GridPartition');
```

Specify the following input membership functions for the generated FIS:

- 3 Gaussian membership functions for the first input variable
- 5 triangular membership functions for the second input variable


```
opt.NumMembershipFunctions = [3 5];
opt.InputMembershipFunctionType = ["gaussmf" "trimf"];
```

Generate the FIS.

```
fis = genfis(inputData,outputData,opt);
```

Plot the input membership functions. Each input variable has the specified number and type of input membership functions, evenly distributed over their input range.

```
[x,mf] = plotmf(fis,'input',1);
subplot(2,1,1)
plot(x,mf)
xlabel('input 1 (gaussmf)')
[x,mf] = plotmf(fis,'input',2);
subplot(2,1,2)
plot(x,mf)
xlabel('input 2 (trimf)')
```



Generate FIS Using Subtractive Clustering

Obtain input and output training data.

```
load clusterDemo.dat
inputData = clusterDemo(:,1:2);
outputData = clusterDemo(:,3);
```

Create a `genfisOptions` option set and specify the range of influence for each data dimension. Specify 0.5 and 0.25 as the range of influence for the first and second input variables. Specify 0.3 as the range of influence for the output data.

```
opt = genfisOptions('SubtractiveClustering',...
    'ClusterInfluenceRange',[0.5 0.25 0.3]);
```

Generate the FIS.

```
fis = genfis(inputData,outputData,opt);
```

The generated FIS contains one rule for each cluster.

```
showrule(fis)
```

```
ans = 3x83 char array
    '1. If (in1 is in1cluster1) and (in2 is in2cluster1) then (out1 is out1cluster1) (1) '
    '2. If (in1 is in1cluster2) and (in2 is in2cluster2) then (out1 is out1cluster2) (1) '
    '3. If (in1 is in1cluster3) and (in2 is in2cluster3) then (out1 is out1cluster3) (1) '
```

Generate FIS Using FCM Clustering

Obtain the input and output data.

```
load clusterDemo.dat
inputData = clusterDemo(:,1:2);
outputData = clusterDemo(:,3);
```

Create a `genfisOptions` option set for FCM Clustering, specifying a Mamdani FIS type.

```
opt = genfisOptions('FCMClustering','FISType','mamdani');
```

Specify the number of clusters.

```
opt.NumClusters = 3;
```

Suppress the display of iteration information to the Command Window.

```
opt.Verbose = 0;
```

Generate the FIS.

```
fis = genfis(inputData,outputData,opt);
```

The generated FIS contains one rule for each cluster.

```
showrule(fis)
```


```
ans = 3x83 char array
    '1. If (in1 is in1cluster1) and (in2 is in2cluster1) then (out1 is out1cluster1) (1) '
    '2. If (in1 is in1cluster2) and (in2 is in2cluster2) then (out1 is out1cluster2) (1) '
    '3. If (in1 is in1cluster3) and (in2 is in2cluster3) then (out1 is out1cluster3) (1) '
```

Plot the input and output membership functions.


```

[x,mf] = plotmf(fis,'input',1);
subplot(3,1,1)
plot(x,mf)
xlabel('Membership Functions for Input 1')
[x,mf] = plotmf(fis,'input',2);
subplot(3,1,2)
plot(x,mf)
xlabel('Membership Functions for Input 2')
[x,mf] = plotmf(fis,'output',1);
subplot(3,1,3)
plot(x,mf)
xlabel('Membership Functions for Output')

```



Create Type-2 Fuzzy Inference System from Data

To create a type-2 FIS from input/output data, you must first create a type-1 FIS using `genfis`.

Load training data and generate a FIS using subtractive clustering.

```

load clusterDemo.dat
inputData = clusterDemo(:,1:2);
outputData = clusterDemo(:,3);
opt = genfisOptions('SubtractiveClustering',...
    'ClusterInfluenceRange',[0.5 0.25 0.3]);

```

```

fisT1 = genfis(inputData,outputData,opt);
fisT1.Outputs

ans =
    fisvar with properties:
        Name: "out1"
        Range: [-0.1274 1.1458]
        MembershipFunctions: [1x3 fismf]

```

Convert the generated FIS to a type-2 FIS.

```

fisT2 = convertToType2(fisT1);

```

Since the initial type-1 FIS is a Sugeno system, only the input MFs are converted to type-2 MFs.

Input Arguments

inputData — Input data

array

Input data, specified as an N -column array, where N is the number of FIS inputs.

`inputData` and `outputData` must have the same number of rows.

outputData — Output data

array

Output data, specified as an M -column array, where M is the number of FIS outputs.

When using grid partitioning, `outputData` must have one column. If you specify more than one column for grid partitioning, `genfis` uses the first column as the output data.

`inputData` and `outputData` must have the same number of rows.

options — FIS generation options

`genfisOptions` option set

FIS generation options, specified as a `genfisOptions` option set. If you do not specify `options`, `genfis` uses a default grid partitioning option set.

You can generate fuzzy systems using one of the following methods, which you specify when you create the option set:

- Grid partitioning — Generate input membership functions by uniformly partitioning the input variable ranges, and create a single-output Sugeno fuzzy system. The fuzzy rule base contains one rule for each input membership function combination.

```

options = genfisOptions('GridPartition');

```

- Subtractive clustering — Generate a Sugeno fuzzy system using membership functions and rules derived from data clusters found using subtractive clustering of input and output data. For more information on subtractive clustering, see `subclust`.

```

options = genfisOptions('SubtractiveClustering');

```

- FCM Clustering — Generate a fuzzy system using membership function and rules derived from data clusters found using FCM clustering of input and output data. For more information on FCM clustering, see `fcm`.

```
options = genfisOptions('FCMClustering');
```

Output Arguments

fis — Fuzzy inference system

`mamfis` object | `sugfis` object

Fuzzy inference system, returned as a `mamfis` or `sugfis` object. The properties of `fis` depend on the type of clustering used and the corresponding options.

Clustering Type	Fuzzy System Type	Input Membership Functions	Fuzzy Rules	Output Membership Functions
Grid Partitioning	Sugeno	Each input variable has evenly distributed input membership function. Specify the number of membership functions using <code>options.NumMembershipFunctions</code> . Specify the membership function type using <code>options.InputMembershipFunctionType</code> .	One rule for each input membership function combination. The consequent of each rule corresponds to a different output membership function.	One output membership function for each fuzzy rule. Specify the membership function type using <code>options.OutputMembershipFunctionType</code> .
Subtractive Clustering	Sugeno	Each input variable has one 'gaussmf' input membership function for each fuzzy cluster.	One rule for each fuzzy cluster	Each output variable has one 'linear' output membership function for each fuzzy cluster.
FCM Clustering	Mamdani or Sugeno	Each input variable has one 'gaussmf' input membership function for each fuzzy cluster.	One rule for each fuzzy cluster	Each output variable has one output membership function for each fuzzy cluster. The membership function type is 'gaussmf' for Mamdani systems and 'linear' for Sugeno systems.

If `fis` is a single-output Sugeno system, you can tune the membership function parameters using the `anfis` function.

Generating a type-2 FIS is not supported by `genfis`. Instead, generating a type-1 FIS and convert it using the `convertToType2` function.

Compatibility Considerations

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

See Also

`genfisOptions` | `anfis` | `fcm` | `subclust`

Introduced in R2017a

genfis1

(To be removed) Generate fuzzy inference system from data using grid partition

Note `genfis1` will be removed in a future release. Use `genfis` instead. For more information, see “Compatibility Considerations”.

Syntax

```

fis = genfis1(data)
fis = genfis1(data,numMFs)
fis = genfis1(data,numMFs,inmfstype)
fis = genfis1(data,numMFs,inmfstype,outmfstype)

```

Description

`fis = genfis1(data)` returns a single-output Sugeno fuzzy inference system (FIS) using a grid partition of the given training data.

`fis = genfis1(data,numMFs)` specifies the number of membership functions to use for each input variable.

`fis = genfis1(data,numMFs,inmfstype)` specifies the type of membership function to use for input variables.

`fis = genfis1(data,numMFs,inmfstype,outmfstype)` specifies the type of membership function to use for output variables.

Examples

Generate FIS Using Grid Partitioning

Generate a FIS using grid partitioning.

```

data = [rand(10,1) 10*rand(10,1)-5 rand(10,1)];
numMFs = [3 7];
mfType = char('pimf','trimf');
fis = genfis1(data,numMFs,mfType);

```

To see the contents of `fis`, use `showfis(fis)`.

Plot the FIS input membership functions.

```

[x,mf] = plotmf(fis,'input',1);
subplot(2,1,1)
plot(x,mf)
xlabel('input 1 (pimf)')
[x,mf] = plotmf(fis,'input',2);
subplot(2,1,2)

```

```
plot(x,mf)
xlabel('input 2 (trimf)')
```

Input Arguments

data — Training data

array

Training data, specified as an array with $M + 1$ columns. The first M columns represent input variable values and the last column represents the output variable value. The number of rows is the number of training data points.

numMFs — Number of membership functions for input variables

2 (default) | vector of positive integers | positive integer

Number of membership functions for input variables, specified as a vector of positive integers. Each element of numMFs corresponds to a given input variable. To use the same number of membership functions for all input variables, specify numMFs as a positive integer.

inmfype — Input variable membership function type

'gbellmf' (default) | string | character vector | character array

Input variable membership function type, specified as a string or character vector to use the same membership function for all input variables, or as a character array to use different membership functions for each input variable.

When you specify a character array, each row specifies the membership function type for one input variable.

The following table lists possible membership functions.

Membership function type	Description	For more information
'gbellmf'	Generalized bell-shaped membership function	gbellmf
'gaussmf'	Gaussian membership function	gaussmf
'gauss2mf'	Gaussian combination membership function	gauss2mf
'trimf'	Triangular membership function	trimf
'trapmf'	Trapezoidal membership function	trapmf
'sigmf'	Sigmoidal membership function	sigmf
'dsigmf'	Difference between two sigmoidal membership functions	dsigmf
'psigmf'	Product of two sigmoidal membership functions	psigmf
'zmf'	Z-shaped membership function	zmf
'pimf'	Pi-shaped membership function	pimf
'smf'	S-shaped membership function	smf

outmfype – Output variable membership function type

'linear' (default) | 'constant'

Output variable membership function type, specified as either 'linear' or 'constant'. The number of membership functions associated with the output is the same as the number of rules generated by `genfis1`.

Output Arguments**fis – Fuzzy inference system**

sugfis object

Fuzzy inference system, returned as a sugfis object.

The following table shows the default inference methods for this fuzzy system.

Inference Method	Default
AND	prod
OR	max
Implication	prod
Aggregation	max
Defuzzification	wtaver

Compatibility Considerations**genfis1 will be removed**

Not recommended starting in R2017a

`genfis1` will be removed in a future release. Use `genfis` instead. There are differences between these functions that require updates to your code.

Update Code

To generate a fuzzy system using grid partitioning, first create a default `genfisOptions` set.

```
opt = genfisOptions('GridPartition');
```

You can modify the options using dot notation. Any options you do not modify remain at their default values.

Then, update your code to use `genfis`. For example, suppose your code has the following form.

```
fis = genfis1(data,numMFs,inmfype,outmfype);
```

Use the following code instead.

```
opt = genfisOptions('GridPartition');
opt.NumMembershipFunctions = numMFs;
opt.InputMembershipFunctionType = inmfype;
opt.OutputMembershipFunctionType = outmfype;
inputData = data(:,end-1);
outputData = data(:,end);
fis = genfis(inputData,outputData,opt);
```

See Also

`genfis` | `anfis` | `genfis2` | `genfis3`

Introduced before R2006a

genfis2

(To be removed) Generate fuzzy inference system from data using subtractive clustering

Note `genfis2` will be removed in a future release. Use `genfis` instead. For more information, see “Compatibility Considerations”.

Syntax

```

fis = genfis2(inputData,outputData,radii)
fis = genfis2(inputData,outputData,radii,xBounds)
fis = genfis2(inputData,outputData,radii,xBounds,options)
fis = genfis2(inputData,outputData,radii,xBounds,options,userCenters)

```

Description

`fis = genfis2(inputData,outputData,radii)` generates a Sugeno-type FIS object from training data using subtractive clustering. Specify the range of influence of the cluster centers using `radii`.

`fis = genfis2(inputData,outputData,radii,xBounds)` specifies data scale factors for normalizing input and output data into a unit hyperbox.

`fis = genfis2(inputData,outputData,radii,xBounds,options)` specifies additional clustering options.

`fis = genfis2(inputData,outputData,radii,xBounds,options,userCenters)` specifies custom cluster centers.

Examples

Specify One Cluster Center Range of Influence For All Data Dimensions

Generate an FIS using subtractive clustering, and specify the cluster center range of influence.

```

Xin = [7*rand(50,1) 20*rand(50,1)-10];
Xout = 5*rand(50,1);
fis = genfis2(Xin,Xout,0.5);

```

`fis` uses a range of influence of 0.5 for all data dimensions.

To see the contents of `fis`, use `showfis(fis)`.

Plot the input membership functions.

```

[x,mf] = plotmf(fis,'input',1);
subplot(2,1,1)
plot(x,mf)
xlabel('Membership Functions for input 1')
[x,mf] = plotmf(fis,'input',2);

```

```
subplot(2,1,2)
plot(x,mf)
xlabel('Membership Functions for input 2')
```

Specify Cluster Center Range of Influence For Each Data Dimension

Suppose the input data has two columns, and the output data has one column. Specify 0.5 and 0.25 as the range of influence for the first and second input data columns. Specify 0.3 as the range of influence for the output data.

```
Xin = [7*rand(50,1) 20*rand(50,1)-10];
Xout = 5*rand(50,1);
fis = genfis2(Xin,Xout,[0.5 0.25 0.3]);
```

Specify Data Hyperbox Scaling Range

Suppose the input data has two columns, and the output data has one column. Specify the scaling range for the inputs and outputs to normalize the data into the [0 1] range. The ranges for the first and second input data columns and the output data are: [-10, 10], [-5, 5], and [0, 20].

```
Xin = [7*rand(50,1) 20*rand(50,1)-10];
Xout = 5*rand(50,1);
fis = genfis2(Xin,Xout,0.5,[-10 -5 0;10 5 20]);
```

Here, the third input argument, 0.5, specifies the range of influence for all data dimensions. The fourth input argument specifies the scaling range for the input and output data.

Input Arguments

inputData — Input data

array

Input data, specified as an N -column array, where N is the number of FIS inputs.

`inputData` and `outputData` must have the same number of rows.

outputData — Output data

array

Output data, specified as an M -column array, where M is the number of FIS outputs.

`inputData` and `outputData` must have the same number of rows.

radii — Range of influence of the cluster center

0.5 (default) | scalar value in the range [0, 1] | vector

Range of influence of the cluster center for each input and output assuming the data falls within a unit hyperbox.

- Scalar value in the range [0, 1] — Use the same influence range for all inputs and outputs.
- Vector — Use different influence ranges for each input and output.

Specifying a smaller range of influence usually creates more and smaller data clusters, producing more fuzzy rules.

xBounds — Data scale factors

array

Data scale factors for normalizing input and output data into a unit hyperbox, specified as a 2-by- N array, where N is the total number of inputs and outputs. Each column of `DataScale` specifies the minimum value in the first row and the maximum value in the second row for the corresponding input or output data set.

When `xBounds` is not specified, the `genfis2` function uses the minimum and maximum values in the data to be clustered.

options — Clustering options

vector

Clustering options, specified as a vector with the following elements.

Options(1) — Squash factor

1.25 (default) | positive scalar

Squash factor for scaling the range of influence of cluster centers, specified as a positive scalar. A smaller squash factor reduces the potential for outlying points to be considered as part of a cluster, which usually creates more and smaller data clusters.

Options(2) — Acceptance ratio

0.5 (default) | scalar value in the range [0, 1]

Acceptance ratio, defined as the fraction of the potential of the first cluster center above which another data point is accepted as a cluster center, specified as a scalar value in the range [0, 1]. The acceptance ratio must be greater than the rejection ratio.

Options(3) — Rejection ratio

0.15 (default) | scalar value in the range [0, 1]

Rejection ratio, defined as the fraction of the potential of the first cluster center below which another data point is rejected as a cluster center, specified as a scalar value in the range [0, 1]. The rejection ratio must be less than the acceptance ratio.

Options(4) — Information display flag

false (default) | true

Information display flag indicating whether to display progress information during clustering, specified as one of the following:

- `false` — Do not display progress information.
- `true` — Display progress information.

userCenters — Custom cluster centers

array

Custom cluster centers, specified as a J -by- N array, where J is the number of clusters and N is the total number of inputs and outputs.

Output Arguments

fis – Fuzzy inference system

sugfis object

Fuzzy inference system, returned as a sugfis object.

The input membership function type is 'gaussmf', and the output membership function type is 'linear'.

The following table shows the default inference methods for this fuzzy system.

Inference Method	Default
AND	prod
OR	propor
Implication	prod
Aggregation	max
Defuzzification	wtaver

Compatibility Considerations

genfis2 will be removed

Not recommended starting in R2017a

genfis2 will be removed in a future release. Use genfis instead. There are differences between these functions that require updates to your code.

Update Code

To generate a fuzzy system using grid partitioning, first create a default genfisOptions set.

```
opt = genfisOptions('SubtractiveClustering');
```

You can modify the options using dot notation. Any options you do not modify remain at their default values.

Then, update your code to use genfis. For example, suppose your code has the following form.

```
fis = genfis2(inputData,outputData,radii,xBounds,options,userCenters);
```

Use the following code instead.

```
opt = genfisOptions('SubtractiveClustering');
opt.ClusterInfluenceRange = radii;
opt.DataScale = xBounds;
opt.SquashFactor = options(1);
opt.AcceptRatio = options(2);
opt.RejectRatio = options(3);
opt.Verbose = options(4);
opt.CustomClusterCenters = userCenters;
fis = genfis(inputData,outputData,opt);
```

See Also

genfis | anfis | subclust | genfis1 | genfis3

Introduced before R2006a

genfis3

(To be removed) Generate fuzzy inference system from data using FCM clustering

Note `genfis3` will be removed in a future release. Use `genfis` instead. For more information, see “Compatibility Considerations”.

Syntax

```
fis = genfis3(inputData,outputData)
fis = genfis3(inputData,outputData,type)
fis = genfis3(inputData,outputData,type,numClusters)
fis = genfis3(inputData,outputData,type,numClusters,options)
```

Description

`fis = genfis3(inputData,outputData)` creates a Sugeno FIS using fuzzy c-means (FCM) clustering by extracting a set of rules that models the training data behavior.

`fis = genfis3(inputData,outputData,type)` generates a FIS of the specified type, either Mamdani or Sugeno.

`fis = genfis3(inputData,outputData,type,numClusters)` specifies the number of clusters to use for the FCM clustering.

`fis = genfis3(inputData,outputData,type,numClusters,options)` specifies additional clustering options.

Examples

Generate Sugeno-Type FIS and Specify Number of Clusters

Create the input and output data.

```
Xin = [7*rand(50,1) 20*rand(50,1)-10];
Xout = 5*rand(50,1);
```

Generate a Sugeno-type FIS with 3 clusters.

```
opt = NaN(4,1);
opt(4) = 0;
fis = genfis3(Xin,Xout,'sugeno',3,opt);
```

The fourth input argument specifies the number of clusters. The fifth input argument, `opt`, specifies the options for the FCM algorithm. The NaN entries of `opt` specify default option values. Setting `opt(4)` to 0 turns off the display of iteration information at the command line.

To see the contents of `fis`, use `showfis(fis)`.

Plot the input membership functions.

```
[x,mf] = plotmf(fis,'input',1);
subplot(2,1,1)
plot(x,mf)
xlabel('Membership Functions for Input 1')
[x,mf] = plotmf(fis,'input',2);
subplot(2,1,2)
plot(x,mf)
xlabel('Membership Functions for Input 2')
```

Input Arguments

inputData — Input data

array

Input data, specified as an N -column array, where N is the number of FIS inputs.

`inputData` and `outputData` must have the same number of rows.

outputData — Output data

array

Output data, specified as an M -column array, where M is the number of FIS outputs.

When using grid partitioning, `outputData` must have one column. If you specify more than one column for grid partitioning, `genfis` uses the first column as the output data.

`inputData` and `outputData` must have the same number of rows.

type — Fuzzy system type

'sugeno' (default) | 'mamdani'

Fuzzy system type, specified as either 'sugeno' or 'mamdani'.

numClusters — Number of FCM clusters

'auto' (default) | positive integer

Number of FCM clusters, specified as 'auto' or a positive integer.

The number of clusters determines the number of rules and membership functions in the generated FIS. `cluster_n` must be an integer or 'auto'. When `cluster_n` is 'auto', the function uses the `subclust` algorithm with a cluster range of influence of 0.5 and the minimum and maximum values of `inputData` and `outputData` as data scale factors to find the number of clusters. See `subclust` for more information.

options — Clustering options

vector

Clustering options, specified as a vector with the following elements:

Option	Description	Default
options (1)	Exponent for the fuzzy partition matrix U , specified as a scalar greater than 1.0. This option controls the amount of fuzzy overlap between clusters, with larger values indicating a greater degree of overlap. If your data set is wide with a lot of overlap between potential clusters, then the calculated cluster centers might be very close to each other. In this case, each data point has approximately the same degree of membership in all clusters. To improve your clustering results, decrease this value, which limits the amount of fuzzy overlap during clustering. For an example of fuzzy overlap adjustment, see “Adjust Fuzzy Overlap in Fuzzy C-Means Clustering” on page 4-7.	2.0
options (2)	Maximum number of iterations, specified as a positive integer.	100
options (3)	Minimum improvement in objective function between two consecutive iterations, specified as a positive scalar.	1e-5
options (4)	Information display flag indicating whether to display the objective function value after each iteration, specified as one of the following: <ul style="list-style-type: none"> • <code>true</code> — Display objective function. • <code>false</code> — Do not display objective function. 	<code>true</code>

If any element of `options` is `NaN`, the default value for that option is used.

The clustering process stops when the maximum number of iterations is reached or when the objective function improvement between two consecutive iterations is less than the specified minimum.

Output Arguments

fis — Fuzzy system

`sugfis` object | `mamfis` object

Fuzzy system, returned as a FIS object.

The input membership function type is `'gaussmf'`. By default, the output membership function type is `'linear'`. However, if you specify `type` as `'mamdani'`, then the output membership function type is `'gaussmf'`.

The following table summarizes the default inference methods.

Inference Method	Default
AND	<code>prod</code>
OR	<code>probor</code>
Implication	<code>prod</code>
Aggregation	<code>sum</code>
Defuzzification	<code>wtaver</code>

Compatibility Considerations

genfis3 will be removed

Not recommended starting in R2017a

genfis3 will be removed in a future release. Use `genfis` instead. There are differences between these functions that require updates to your code.

Update Code

To generate a fuzzy system using grid partitioning, first create a default `genfisOptions` set.

```
opt = genfisOptions('FCMClustering');
```

You can modify the options using dot notation. Any options you do not modify remain at their default values.

Then, update your code to use `genfis`. For example, suppose your code has the following form.

```
fis = genfis3(inputData,outputData,type,cluster_n,fcoptions);
```

Use the following code instead.

```
opt = genfisOptions('FCMClustering');
opt.FISType = type;
opt.NumClusters = cluster_n;
opt.Exponent = fcoptions(1);
opt.MaxNumIteration = fcoptions(2);
opt.MinImprovement = fcoptions(3);
opt.Verbose = fcoptions(4);
fis = genfis(inputData,outputData,opt);
```

See Also

`genfis` | `anfis` | `fcm` | `genfis1` | `genfis2`

Introduced before R2006a

genfisOptions

Option set for `genfis` function

Syntax

```
opt = genfisOptions(clusteringType)
opt = genfisOptions(clusteringType,Name,Value)
```

Description

`opt = genfisOptions(clusteringType)` creates a default options object for generating a fuzzy inference system using `genfis`. The options object, `opt`, contains different options that depend on the specified clustering algorithm, `clusteringType`. Use dot notation to modify this option set for your specific application. Options that you do not modify retain their default values.

`opt = genfisOptions(clusteringType,Name,Value)` creates an option set with options specified by one or more `Name,Value` pair arguments.

Examples

Specify Options for FIS Generation

Create a default option set for the grid partitioning generation method.

```
opt = genfisOptions('GridPartition');
```

Modify the options using dot notation. For example, specify 3 membership functions for the first input and 4 membership functions for the second input.

```
opt.NumMembershipFunctions = [3 4];
```

You can also specify options when creating the option set. For example, create an option set for FCM clustering using 4 clusters.

```
opt2 = genfisOptions('FCMClustering','NumClusters',4);
```

Input Arguments

`clusteringType` — Clustering method

"GridPartition" | "SubtractiveClustering" | "FCMClustering"

Clustering method for defining membership functions and fuzzy rules, specified as one of the following:

- "GridPartition" — Generate input membership functions by uniformly partitioning the input variable ranges, and create a single-output Sugeno fuzzy system. The fuzzy rule base contains one rule for each input membership function combination.

- "SubtractiveClustering" — Generate a Sugeno fuzzy system using membership functions and rules derived from data clusters found using subtractive clustering of input and output data. For more information on subtractive clustering, see `subclust`.
- "FCMClustering" — Generate a fuzzy system using membership function and rules derived from data clusters found using FCM clustering of input and output data. For more information on FCM clustering, see `fc`.

Name-Value Pair Arguments

Specify optional pairs of arguments as `Name1=Value1, ..., NameN=ValueN`, where `Name` is the argument name and `Value` is the corresponding value. Name-value arguments must appear after other arguments, but the order of the pairs does not matter.

Before R2021a, use commas to separate each name and value, and enclose Name in quotes.

Example: `opt = genfis("GridPartition", NumMembershipFunctions=3)`

Before R2021a, use commas to separate each name and value, and enclose Name in quotes.

Example: `opt = genfis("GridPartition", "NumMembershipFunctions", 3)`

Grid Partitioning Options

NumMembershipFunctions — Number of input membership functions

2 (default) | integer greater than 1 | vector of integers greater than 1

Number of input membership functions for each input variable, specified as one of the following values.

- Integer greater than 1 — Specify the same number of membership functions for all inputs.
- Vector of integer greater than 1 with length equal to the number of inputs — Specify a different number of membership functions for each input.

InputMembershipFunctionType — Input membership function type

'gbellmf' (default) | 'gaussmf' | 'trimf' | 'trapmf' | character vector | string array | ...

Input membership function type, specified as one of the following values.

- Character vector or string — Specify one of the following membership function types for all inputs.

Membership function type	Description	For more information
'gbellmf'	Generalized bell-shaped membership function	gbellmf
'gaussmf'	Gaussian membership function	gaussmf
'gauss2mf'	Gaussian combination membership function	gauss2mf
'trimf'	Triangular membership function	trimf
'trapmf'	Trapezoidal membership function	trapmf
'linsmf'	Linear s-shaped membership function	linsmf

Membership function type	Description	For more information
'linzmf'	Linear z-shaped membership function	linzmf
'sigmf'	Sigmoidal membership function	sigmf
'dsigmoid'	Difference between two sigmoidal membership functions	dsigmoid
'psigmoid'	Product of two sigmoidal membership functions	psigmoid
'zmf'	Z-shaped membership function	zmf
'pimf'	Pi-shaped membership function	pimf
'smf'	S-shaped membership function	smf
Character vector or string	Name of a custom membership function in the current working folder or on the MATLAB path	"Build Fuzzy Systems Using Custom Functions" on page 2-40

- Character array or string array — Specify a different membership function type for each input. For example, specify different membership functions for a three-input system:

```
["gbellmf", "gaussmf", "trimf"]
```

OutputMembershipFunctionType — Output membership function type

'linear' (default) | 'constant'

Output membership function type for a single-output Sugeno system, specified as one of the following values.

- 'linear' — The output of each rule is a linear function of the input variables, scaled by the antecedent result value.
- 'constant' — The output of each rule is a constant, scaled by the antecedent result value.

Subtractive Clustering Options

ClusterInfluenceRange — Range of influence of the cluster center

0.5 (default) | scalar value in the range [0, 1] | vector

Range of influence of the cluster center for each input and output assuming the data falls within a unit hyperbox, specified as one of the following values.

- Scalar value in the range [0 1] — Use the same influence range for all inputs and outputs.
- Vector — Use different influence ranges for each input and output.

Specifying a smaller range of influence usually creates more and smaller data clusters, producing more fuzzy rules.

DataScale — Data scale factors

'auto' (default) | 2-by-*N* array

Data scale factors for normalizing input and output data into a unit hyperbox, specified as a 2-by-*N* array, where *N* is the total number of inputs and outputs. Each column of `DataScale` specifies the minimum value in the first row and the maximum value in the second row for the corresponding input or output data set.

When `DataScale` is `'auto'`, the `genfis` command uses the actual minimum and maximum values in the data to be clustered.

SquashFactor — Squash factor

1.25 (default) | positive scalar

Squash factor for scaling the range of influence of cluster centers, specified as the comma-separated pair consisting of `'SquashFactor'` and a positive scalar. A smaller squash factor reduces the potential for outlying points to be considered as part of a cluster, which usually creates more and smaller data clusters.

AcceptRatio — Acceptance ratio

0.5 (default) | scalar value in the range [0, 1]

Acceptance ratio, defined as a fraction of the potential of the first cluster center, above which another data point is accepted as a cluster center, specified as a scalar value in the range [0, 1]. The acceptance ratio must be greater than the rejection ratio.

RejectRatio — Rejection ratio

0.15 (default) | scalar value in the range [0, 1]

Rejection ratio, defined as a fraction of the potential of the first cluster center, below which another data point is rejected as a cluster center, specified as a scalar value in the range [0, 1]. The rejection ratio must be less than acceptance ratio.

Verbose — Information display flag

false (default) | true

Information display flag indicating whether to display progress information during clustering, specified as one of the following values.

- `false` — Do not display progress information.
- `true` — Display progress information.

CustomClusterCenters — Custom cluster centers

[] (default) | *C*-by-*N* array

Custom cluster centers, specified as a *C*-by-*N* array, where *C* is the number of clusters and *N* is the total number of inputs and outputs.

FCM Clustering Options

FISType — Fuzzy inference system type

'sugeno' (default) | 'mamdani'

Fuzzy inference system type, specified as one of the following values.

- `'sugeno'` — Sugeno-type fuzzy system
- `'mamdani'` — Mamdani-type fuzzy system

For more information on the types of fuzzy inference systems, see “Mamdani and Sugeno Fuzzy Inference Systems” on page 2-2.

NumClusters — Number of clusters

'auto' | integer greater than 1

Number of clusters to create, specified as 'auto' or an integer greater than 1. When NumClusters is 'auto', the `genfis` command estimates the number of clusters using subtractive clustering with a cluster influence range of 0.5.

NumClusters determines the number of rules and membership functions in the generated FIS.

Exponent — Exponent for the fuzzy partition matrix

2.0 (default) | scalar greater than 1.0

Exponent for the fuzzy partition matrix, specified as a scalar greater than 1.0. This option controls the amount of fuzzy overlap between clusters, with larger values indicating a greater degree of overlap.

If your data set is wide with significant overlap between potential clusters, then the calculated cluster centers can be very close to each other. In this case, each data point has approximately the same degree of membership in all clusters. To improve your clustering results, decrease this value, which limits the amount of fuzzy overlap during clustering.

For an example of fuzzy overlap adjustment, see “Adjust Fuzzy Overlap in Fuzzy C-Means Clustering” on page 4-7.

MaxNumIteration — Maximum number of iterations

100 (default) | positive integer

Maximum number of iterations, specified as a positive integer.

MinImprovement — Minimum improvement in objective function

1e-5 (default) | positive scalar

Minimum improvement in objective function between two consecutive iterations, specified as a positive scalar.

Verbose — Information display flag

true (default) | false

Information display flag indicating whether to display the objective function value after each iteration, specified as one of the following values.

- true — Display objective function.
- false — Do not display objective function.

Output Arguments

opt — Options for genfis function

GridPartitionOptions object | SubtractiveClusteringOptions object | FCMClusteringOptions object

Options for `genfis` function, returned as one of the following objects.

- GridPartitionOptions — When clusteringType is 'GridPartition'
- SubtractiveClusteringOptions — When clusteringType is 'SubtractiveClustering'
- FCMClusteringOptions — When clusteringType is 'FCMClustering'

See Also

genfis | fcm | subclust

Introduced in R2017a

gensurf

Generate fuzzy inference system output surface

Syntax

```
gensurf(fis)  
gensurf(fis,options)  
[X,Y,Z] = gensurf( ___ )
```

Description

`gensurf(fis)` generates the output surface for the fuzzy inference system, `fis`, plotting the first output variable against the first two input variables. For fuzzy systems with more than two inputs, the remaining input variables use the midpoints of their respective ranges as reference values.

`gensurf(fis,options)` generates the output surface using the specified `options`. To generate a surface using different inputs or outputs, or to specify nondefault plotting options, use this syntax.

`[X,Y,Z] = gensurf(___)` returns the variables that define the output surface for any of the previous syntaxes and suppresses the surface plot.

Examples

Generate FIS Output Surface


Load a fuzzy inference system.

```
fis = readfis('tipper');
```

This fuzzy system has two inputs and one output.

Generate the output surface for the system.

```
gensurf(fis)
```

Generate FIS Output Surface for Second Output

Load a fuzzy inference system with two inputs and two outputs.


```
fis = readfis('mam22.fis');
```

Create a surface generation option set, specifying the second output as the output to plot. By default, this output is plotted against the first two input variables.

```
opt = gensurfOptions('OutputIndex',2);
```

Plot the surface, using the specified option set.

```
gensurf(fis,opt)
```



Specify Reference Inputs for Surface Plot

Load a fuzzy inference system with four inputs and one output.

```
fis = readfis('multiInput.fis');
```

Create a default `gensurfOptions` object..

```
opt = gensurfOptions;
```


Specify plotting options to:

- Plot the output against the second and third input variable.
- Use 20 grid points for both inputs.
- Fix the first and fourth inputs at -0.5 and 0.1 respectively. Set the reference values for the second and third inputs to `NaN`.

```
opt.InputIndex = [2 3];
opt.NumGridPoints = 20;
opt.ReferenceInputs = [-0.5 NaN NaN 0.1];
```

Plot the output surface.

```
gensurf(fis,opt)
```



Return Surface Values and Suppress Plot

Load a fuzzy inference system.

```
fis = readfis('tipper');
```

Generate the output surface, returning the surface data.

```
[X,Y,Z] = gensurf(fis);
```

The output values, Z, are the FIS output evaluated at the corresponding X and Y grid points.

Input Arguments

fis — Fuzzy inference system

mamfis object | sugfis object | mamfistype2 object | sugfistype2 object

Fuzzy inference system, specified as one of the following:

- mamfis object — Mamdani fuzzy inference system
- sugfis object — Sugeno fuzzy inference system
- mamfistype2 object — Type-2 Mamdani fuzzy inference system

- `sugfistype2` object — Type-2 Sugeno fuzzy inference system

options — Surface generation options

`gensurfOptions` option set

Surface generation options, specified as a `gensurfOptions` option set.

Output Arguments

X — Grid values for first input variable

array | column vector

Grid values for first input variable, returned as one of the following:

- M -by- N array, where N and M are the number of grid points for the first and second inputs, respectively; that is `options.NumGridPoints = [N M]`. Each column of X contains one grid point value, repeated for every row.
- P -element column vector, where P is the number of grid points specified for a single input variable; that is `options.NumGridPoints = P`. Each element of contains one grid point value. This case applies when `fis` has only one input variable.

Y — Grid values for second input variable

array | []

Grid values for second input variable, returned as one of the following:

- M -by- N array, where N and M are the number of grid points for the first and second inputs respectively; that is `options.NumGridPoints = [N M]`. Each row of Y contains one grid point value, repeated for every column.
- [] when you specify only one input variable; that is, if you specify `options.InputIndex` as an integer.

Z — Surface output values

array | vector

Surface output values for the output variable of `fis` specified by `options.OutputIndex`, returned as one of the following:

- M -by- N array, where N and M are the number of grid points for the first and second inputs respectively; that is `options.NumGridPoints = [N M]`. Each element of Z is the value of the FIS output, evaluated at the corresponding X and Y input values. For example, for a two-input system:

$$Z(i,j) = \text{evalfis}(\text{fis}, [X(i,j) \ Y(i,j)]);$$
- P -element column vector, where P is the number of grid points specified for a single input variable; that is `options.NumGridPoints = P`. Each element of Z is the value of the FIS output evaluated at the corresponding X input value.

When computing the value of Z , `gensurf` sets the values of any inputs not specified by `options.InputIndex` to their corresponding reference values, as specified in `options.ReferenceInputs`.

Compatibility Considerations

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

See Also

`gensurfOptions` | `evalfis` | `surfview`

Introduced before R2006a

getfis

(To be removed) Get fuzzy system properties

Note `getfis` will be removed in a future release. Access fuzzy inference system properties using dot notation instead. For more information, see “Compatibility Considerations”.

Syntax

```
getfis(sys)
```

```
fisInfo = getfis(sys)  
fisInfo = getfis(sys, fisProperty)
```

```
varInfo = getfis(sys, varType, varIndex)  
varInfo = getfis(sys, varType, varIndex, varProperty)
```

```
mfInfo = getfis(sys, varType, varIndex, 'mf', mfIndex)  
mfInfo = getfis(sys, varType, varIndex, 'mf', mfIndex, mfProperty)
```

Description

`getfis(sys)` prints the properties of the fuzzy inference system `sys`, to the Command Window.

`fisInfo = getfis(sys)` returns the properties of the specified fuzzy inference system.

`fisInfo = getfis(sys, fisProperty)` returns the value of the specified property of the fuzzy inference system.

`varInfo = getfis(sys, varType, varIndex)` returns the properties of the specified input or output variable of a fuzzy inference system.

`varInfo = getfis(sys, varType, varIndex, varProperty)` returns the value of the specified variable property.

`mfInfo = getfis(sys, varType, varIndex, 'mf', mfIndex)` returns the properties of the specified membership function of an input or output variable.

`mfInfo = getfis(sys, varType, varIndex, 'mf', mfIndex, mfProperty)` returns the value of the specified membership function property.

Examples

Display Properties of Fuzzy Inference System

Load a fuzzy inference system.

```
sys = readfis('tipper');
```

Display the system properties.

```
getfis(sys)

Name      = tipper
Type      = mamdani
NumInputs = 2
InLabels  =
    service
    food
NumOutputs = 1
OutLabels =
    tip
NumRules  = 3
AndMethod = min
OrMethod  = max
ImpMethod = min
AggMethod = max
DefuzzMethod = centroid
```

Obtain Fuzzy Inference System Properties

Load fuzzy system.

```
sys = readfis('tipper');
```

Obtain the system properties.

```
prop = getfis(sys);
```

To obtain the value of a given property, specify the property name. For example, obtain the type of the fuzzy system.

```
type = getfis(sys, 'type');
```

Obtain Variable Properties

Load fuzzy system.

```
sys = readfis('tipper');
```

Obtain the properties of the first input variable.

```
prop = getfis(sys, 'input', 1);
```

To obtain the value of a given property, specify the property name. For example, obtain the range of the output variable.

```
range = getfis(sys, 'output', 1, 'range');
```

Obtain Membership Function Properties

Load fuzzy system.

```
sys = readfis('tipper');
```

For the second input variable, obtain the properties of its first membership function.

```
prop = getfis(sys, 'input', 2, 'mf', 1);
```

To obtain the value of a given property, specify the property name. For example, obtain the parameters of the second membership function of the output variable.

```
params = getfis(sys, 'output', 1, 'mf', 2, 'params');
```

Input Arguments

sys — Fuzzy inference system

FIS structure

Fuzzy inference system, specified as an FIS structure.

fisProperty — Fuzzy inference system property

'name' | 'type' | 'numInputs' | 'numOutputs' | ...

Fuzzy inference system property, specified as one of the following:

- 'name' — FIS name
- 'type' — FIS type
- 'numInputs' — Number of inputs
- 'numOutputs' — Number of outputs
- 'numRules' — Number of fuzzy rules.
- 'andMethod' — And method
- 'orMethod' — Or method
- 'defuzzMethod' — Defuzzification method
- 'impMethod' — Implication method
- 'aggMethod' — Aggregation method
- 'ruleList' — List of fuzzy rules

varType — Variable type

'input' | 'output'

Variable type, specified as either 'input' or 'output', for input and output variables, respectively.

varIndex — Variable index

positive integer

Variable index, specified as a positive integer.

varProperty — Variable property

'name' | 'range' | 'nummfs'

Variable property, specified as one of the following:

- 'name' — Variable name
- 'range' — Variable value range

- 'nummfs' — Number of membership functions

mfIndex — Membership function index

positive integer

Membership function index, specified as a positive integer.

mfProperty — Membership function property

'name' | 'type' | 'params'

Membership function property, specified as one of the following:

- 'name' — Membership function name
- 'type' — Membership function type
- 'params' — Membership function parameters

For more information on membership functions, see “Membership Functions” on page 1-9.

Output Arguments

fisInfo — Fuzzy inference system information

structure | character vector | nonnegative integer | array

Fuzzy inference system information, returned as a structure, character vector, nonnegative integer, or array, depending on the value of `fisProperty`.

If you do not specify `fisProperty`, then `fisInfo` is returned as a structure with the following fields.

Field	Description
name	FIS name, returned as a character vector.
type	FIS type, returned as a character vector.
andMethod	AND fuzzy operator method, returned as a character vector.
orMethod	OR fuzzy operator method, returned as a character vector.
defuzzMethod	Defuzzification method, returned as a character vector.
impMethod	Implication method, returned as a character vector.
aggMethod	Aggregation method, returned as a character vector.
input	Input variable information, returned as a structure or structure array. Each input variable structure contains the following fields: <ul style="list-style-type: none"> • name — Variable name • range — Variable range • mf — Membership function names

Field	Description
output	Output variable information, returned as a structure or structure array. Each output variable structure contains the following fields: <ul style="list-style-type: none"> • name — Variable name • range — Variable range • mf — Membership function names
rule	Fuzzy rule list, returned as a structure or structure array. Each rule structure contains the following fields: <ul style="list-style-type: none"> • antecedent — Input membership function indices • consequent — Output membership function indices • weight — Rule weight • connection — Fuzzy operator: 1 (AND), 2 (OR)

Otherwise, the value of `fisInfo` depends on the value of `fisProperty` according to the following table.

<code>fisProperty</code>	<code>fisInfo</code>
'name'	FIS name, returned as a character vector.
'type'	FIS type, returned as one of the following: <ul style="list-style-type: none"> • 'mamdani' — Mamdani-type fuzzy system • 'sugeno' — Sugeno-type fuzzy system
'numinputs'	Number of input variables, returned as a nonnegative integer.
'numiutputs'	Number of output variables, returned as a nonnegative integer.
'numrules'	Number of fuzzy rules, returned as a nonnegative integer.
'andmethod'	AND fuzzy operator method, returned as one of the following: <ul style="list-style-type: none"> • 'min' — Minimum of fuzzified input values • 'prod' — Product of fuzzified input values • Character vector — Name of a custom AND function in the current working folder or on the MATLAB path
'ormethod'	OR fuzzy operator method, returned as one of the following: <ul style="list-style-type: none"> • 'max' — Maximum of fuzzified input values • 'probor' — Probabilistic OR of fuzzified input values • Character vector — Name of a custom OR function in the current working folder or on the MATLAB path

fisProperty	fisInfo
'defuzzmethod'	<p>Defuzzification method for computing crisp output values, returned as one of the following for Mamdani systems:</p> <ul style="list-style-type: none"> • 'centroid' — Centroid of the area under the output fuzzy set • 'bisector' — Bisector of the area under the output fuzzy set • 'mom' — Mean of the values for which the output fuzzy set is maximum • 'lom' — Largest value for which the output fuzzy set is maximum • 'som' — Smallest value for which the output fuzzy set is maximum <p>For Sugeno systems, specify the defuzzification method as one of the following:</p> <ul style="list-style-type: none"> • 'wtaver' — Weighted average of all rule outputs • 'wtsum' — Weighted sum of all rule outputs <p>The defuzzification method can also be returned as a character vector that contains the name of a custom defuzzification function in the current working folder or on the MATLAB path.</p>
'impmethod'	<p>Implication method for computing consequent fuzzy set, returned as one of the following:</p> <ul style="list-style-type: none"> • 'min' — Truncate the consequent membership function at the antecedent result value. • 'prod' — Scale the consequent membership function by the antecedent result value. • Character vector — Name of a custom implication function in the current working folder or on the MATLAB path
'aggmethod'	<p>Aggregation method for combining rule consequents, returned as one of the following:</p> <ul style="list-style-type: none"> • 'max' — Maximum of consequent fuzzy sets • 'sum' — Sum of consequent fuzzy sets • 'probor' — Probabilistic OR of consequent fuzzy sets • Character vector — Name of a custom aggregation function in the current working folder or on the MATLAB path.

fisProperty	fisInfo
'rulelist'	<p>Fuzzy rule list, returned as an array. For each fuzzy rule, the rule list contains one row with the following columns:</p> <ul style="list-style-type: none"> • N_u columns of input membership function indices, where N_u is the number of inputs. If a given variable is not included in a rule, the corresponding column entry is 0. Negative values indicate a NOT operation. • N_y columns of output membership function indices, where N_y is the number of outputs. If a given variable is not included in a rule, the corresponding column entry is 0. Negative values indicate a NOT operation. • Rule weight • Fuzzy operator: 1 (AND), 2 (OR)

varInfo – Variable information

structure | character vector | nonnegative integer | row vector of length 2

Variable information, returned as a structure, nonnegative integer, character vector, or row vector, depending on the value of varProperty.

If you do not specify varProperty, then varInfo is returned as a structure with the following fields.

Field	Description
Name	Variable name, returned as a character vector.
NumMFs	Number of membership functions, returned as a nonnegative integer.
mf1, mf2, ..., mfN	Membership function names, returned as character vectors. mfInfo contains one field for each membership function.
range	Variable range, returned as a row vector of length 2.

Otherwise, the value of varInfo depends on the value of varProperty according to the following table.

varProperty	varInfo
'name'	Variable name, returned as a character vector.
'nummfs'	Number of membership functions, returned as a nonnegative integer.
'range'	Variable range, returned as a row vector of length 2.

mfInfo – Membership function information

structure | character vector | row vector

Membership function information, returned as a structure, character vector, or row vector, depending on the value of mfProperty.

If you do not specify mfProperty, then mfInfo is returned as a structure with the following fields.

Field	Description
Name	Membership function name, returned as a character vector.
Type	Membership function type, returned as a character vector.
params	Membership function parameters, returned as a row vector.

Otherwise, the value of `mfInfo` depends on the value of `mfProperty` according to the following table.

mfProperty	mfInfo
'name'	Membership function name, returned as a character vector.
'type'	Membership function type, returned as a character vector.
'params'	Membership function parameters, returned as a row vector.

For more information on membership function, see “Membership Functions” on page 1-9.

Compatibility Considerations

getfis will be removed

Not recommended starting in R2018b

`getfis` will be removed in a future release. Access fuzzy inference system properties using dot notation instead. There are differences between these approaches that require updates to your code.

Update Code

This table shows some typical usages of `getfis` for accessing fuzzy inference system properties and how to update your code to use dot notation instead.

If your code has this form:	Use this code instead:
<code>get(fis, 'andmethod')</code>	<code>fis.AndMethod</code>
<code>getfis(fis, 'input', 1)</code>	<code>fis.Inputs(1)</code>
<code>getfis(fis, 'input', 1, 'name')</code>	<code>fis.Inputs(1).Name</code>
<code>getfis(fis, 'input', 2, 'mf', 1)</code>	<code>fis.Inputs(2).MembershipFunctions(1)</code>
<code>getfis(fis, 'input', 2, 'mf', 1, ... params)</code>	<code>fis.Inputs(2).MembershipFunctions(1).Parameters</code>

Previously, fuzzy inference systems were represented as structures. Now, fuzzy inference systems are represented as objects. Fuzzy inference system object properties have different names than the corresponding structure fields. For more information on fuzzy inference system objects, see `mamfis` and `sugfis`.

See Also

`setfis` | `showfis`

Introduced before R2006a

getFISCodeGenerationData

Create homogeneous fuzzy inference system structure

Syntax

```
fisOut = getFISCodeGenerationData(fisIn)
fisOut = getFISCodeGenerationData(fisIn,"FuzzySetType",setType)
```

Description

To generate code for evaluating a fuzzy inference system using MATLAB Coder, you must convert your fuzzy inference system object into a homogeneous structure using `getFISCodeGenerationData`.

`fisOut = getFISCodeGenerationData(fisIn)` converts a type-1 fuzzy inference system `fisIn` into a homogeneous structure `fisOut`. `fisIn` can be a FIS object or the name of a `.fis` file.

`fisOut = getFISCodeGenerationData(fisIn,"FuzzySetType",setType)` specifies the type of membership functions used in `fisIn`.

Examples

Convert FIS Object into Homogeneous Structure

Create a fuzzy inference system. For this example, load a fuzzy system from a file.

```
fisObject = readfis('tipper');
```

Convert the resulting `mamfis` object into a homogeneous structure.

```
fisStructure = getFISCodeGenerationData(fisObject);
```

In this structure, if a field is a structure array, all the elements of that array are the same size. For example, consider the elements of input variable array `fisStructure.input`.

```
fisStructure.input(1)
```

```
ans = struct with fields:
    name: 'service'
origNameLength: 7
    range: [0 10]
        mf: [1x3 struct]
origNumMF: 3
```

```
fisStructure.input(2)
```

```
ans = struct with fields:
    name: 'food'
origNameLength: 4
    range: [0 10]
```

```
mf: [1x3 struct]
origNumMF: 2
```

The name fields are character vectors of the same length. Also, even though the second input variable has only two membership functions, the mf fields both contain three membership function structures. The original number of membership functions for a given input variable is stored in the origNumMF field.

Load Fuzzy Inference System from File into Homogeneous Structure

Load the fuzzy inference system saved in the file `tipper.fis` into a homogeneous structure.

```
fis = getFISCodeGenerationData('tipper.fis');
```

Convert Type-2 FIS Object into Homogeneous Structure

Create a type-2 fuzzy inference system. For this example, create a default FIS with three inputs and two outputs.

```
fisObject = mamfistype2('NumInputs',3,'NumOutputs',2);
```

Convert the resulting `mamfistype2` object into a homogeneous structure.

```
fisStructure = getFISCodeGenerationData(fisObject,'FuzzySetType','type2');
```

Input Arguments

fisIn — Input fuzzy inference system

`mamfis` object | `sugfis` object | `mamfistype2` object | `sugfistype2` object | string | character vector

Input fuzzy inference system, specified as one of the following:

- `mamfis`, `sugfis`, `mamfistype2`, or `sugfistype2` object. `getFISCodeGenerationData` supports fuzzy inference system objects for simulation only.
- String or character vector specifying a `.fis` file in the current working folder or on the MATLAB path. `getFISCodeGenerationData` supports fuzzy inference system file names for both simulation and code generation.

If `fisIn` is either a `mamfistype2` or `sugfistype2` object, then you must specify `setType` as `"type2"`.

When `getFISCodeGenerationData` loads a fuzzy system that uses custom functions, it writes additional files to the current folder to support code generation for the custom functions.

setType — Type of membership functions

`"type1"` (default) | `"type2"`

Type of membership functions used in `fisIn`, specified as one of the following:

- "type1" — Type-1 membership functions
- "type2" — Type-2 membership functions

Output Arguments

fisOut — Output fuzzy inference system

homogeneous structure

Output fuzzy inference system, returned as a homogeneous structure. In the homogeneous structure, if a field is a structure array, all the elements of that array are the same size. For example, in the input variable array `fisOut.input`:

- Names of all the variables are character vectors of the same length.
- Lengths of the membership function arrays for all variables are the same.

For any character vectors or structure arrays that are padded to increase their lengths, the original lengths of these elements are saved within the structure.

The `fisOut` structure is different from the structure created using `convertToStruct`.

Note Modifying the fields of `fisOut` can produce unexpected results. Instead, modify `fisIn` and call `getFISCodeGenerationData` again.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using MATLAB® Coder™.

Usage notes and limitations:

- `getFISCodeGenerationData` supports fuzzy inference system objects for simulation only. To generate code for `getFISCodeGenerationData`, specify the input fuzzy inference system using a file name.
- It is good practice to not use `getFISCodeGenerationData` within a MATLAB Function block. This function is a utility function for generating code for evaluating a fuzzy inference system using MATLAB Coder.

See Also

`mamfis` | `sugfis` | `mamfistype2` | `sugfistype2` | `evalfis` | `evalfisOptions`

Introduced in R2018b

getTunableSettings

Obtain tunable settings from fuzzy inference system

Syntax

```
in = getTunableSettings(fis)
[~,out] = getTunableSettings(fis)
[~,~,rule] = getTunableSettings(fis)
[in,out,rule] = getTunableSettings(fis)
[ ___ ] = getTunableSettings(fis,'AsymmetricLag',true)
```

Description

`in = getTunableSettings(fis)` returns tunable settings of input variables of the fuzzy system `fis`.

`[~,out] = getTunableSettings(fis)` returns tunable settings of output variables of the fuzzy system `fis`.

`[~,~,rule] = getTunableSettings(fis)` returns tunable settings of rules of the fuzzy system `fis`.

`[in,out,rule] = getTunableSettings(fis)` returns tunable settings of inputs, outputs, and rules of the fuzzy system `fis`.

`[___] = getTunableSettings(fis,'AsymmetricLag',true)` returns tunable settings which allow asymmetric lower membership function lag values. This syntax is supported only when `fis` is a type-2 fuzzy inference system.

Examples

Obtain Tunable Settings from FIS

Create two fuzzy inference systems, and define the connection between the two.

```
fis1 = mamfis('Name','fis1','NumInputs',2,'NumOutputs',1);
fis2 = sugfis('Name','fis2','NumInputs',2,'NumOutputs',1);
con = ["fis1/output1" "fis2/input1"];
```

Create a tree of fuzzy inference systems.

```
tree = fistree([fis1 fis2],con);
```

Obtain the tunable settings of inputs, outputs, and rules of the fuzzy inference system.

```
[in,out,rule] = getTunableSettings(tree)
```

`in=4x1 object`
4x1 VariableSettings array with properties:

```

    Type
    VariableName
    MembershipFunctions
    FISName

out=2x1 object
    2x1 VariableSettings array with properties:

    Type
    VariableName
    MembershipFunctions
    FISName

rule=18x1 object
    16x1 RuleSettings array with properties:

    Index
    Antecedent
    Consequent
    FISName
    :
```

You can use dot notation to specify tunable settings.

For the first membership function of input 1:

- do not tune parameter 1,
- set the minimum ranges of the last two parameters to 0,
- and set the maximum ranges of the last two parameters to 1.

```

in(1).MembershipFunctions(1).Parameters.Free(1) = false;
in(1).MembershipFunctions(1).Parameters.Minimum(2:end) = 0;
in(1).MembershipFunctions(1).Parameters.Maximum(2:end) = 1;
```

For the first rule:

- set input 1 membership function index non-tunable,
- allow NOT logic for input 2 membership function index,
- and do not ignore output 1 membership function index.

```

rule(1).Antecedent.Free(1) = false;
rule(1).Antecedent.AllowNot(2) = true;
rule(1).Consequent.AllowEmpty(1) = false;
```

Obtain Tunable Settings of Input and Output Variables from FIS

Create two fuzzy inference systems, and define the connection between the two.

```

fis1 = mamfis('Name', 'fis1', 'NumInputs', 2, 'NumOutputs', 1);
fis2 = sugfis('Name', 'fis2', 'NumInputs', 2, 'NumOutputs', 1);
con = ["fis1/output1" "fis2/input1"];
```

Create a tree of fuzzy inference systems.

```
tree = fistree([fis1 fis2],con);
```

Obtain the tunable settings of input and output variables of the fuzzy inference system.

```
[in,out] = getTunableSettings(tree)
```

in=4x1 object

4x1 VariableSettings array with properties:

```
Type
VariableName
MembershipFunctions
FISName
```

out=2x1 object

2x1 VariableSettings array with properties:

```
Type
VariableName
MembershipFunctions
FISName
```

You can use dot notation to specify the tunable settings of input and output variables.

For the first membership function of input 1, set the first and third parameters to tunable.

```
in(1).MembershipFunctions(1).Parameters.Free = [1 0 1];
```

For the first membership function of input 2, set the minimum parameter range to 0.

```
in(2).MembershipFunctions(1).Parameters.Minimum = 0;
```

For the first membership function of output 2, set the maximum parameter range to 1.

```
out(2).MembershipFunctions(1).Parameters.Maximum = 1;
```

Obtain Tunable Settings of Input and Output Variables from Type-2 FIS

Create a type-2 fuzzy inference system.

```
fis = mamfistype2('Name','fis1','NumInputs',2,'NumOutputs',1);
```

Obtain the tunable settings of the input and output variables of the fuzzy inference system.

```
[in,out] = getTunableSettings(fis);
```

You can use dot notation to specify the tunable settings of the membership functions of the input and output variables.

For the first membership function of input 1, set the first and third upper membership function parameters as tunable.

```
in(1).MembershipFunctions(1).UpperParameters.Free = [1 0 1];
```

For the first membership function of input 2, set the tunable range of the lower membership function scale to be between 0.7 and 0.9.

```
in(2).MembershipFunctions(1).LowerScale.Minimum = 0.7;
in(2).MembershipFunctions(1).LowerScale.Maximum = 0.9;
```

For the first membership function of output 1, set the tunable range of the lower membership function lag to be between 0.1 and 0.4.

```
in(2).MembershipFunctions(1).LowerLag.Minimum = 0.1;
in(2).MembershipFunctions(1).LowerLag.Maximum = 0.4;
```

Specify Tunability of Parameter Settings

Create a fuzzy inference system, and define the tunable parameter settings of inputs, outputs, and rules.

Create a FIS, and obtain its tunable settings.

```
fis = mamfis("NumInputs",2,"NumOutputs",2);
[in,out,rule] = getTunableSettings(fis);
```

You can specify all the input variables, output variables, or rules as tunable or nontunable. For example, set all the output variable settings as nontunable.

```
out = setTunable(out,0);
```

You can set the tunability of individual variables or rules. For example, set the first input variable as nontunable.

```
in(1) = setTunable(in(1),0);
```

You can set individual membership functions as nontunable. For example, set the first membership function of input 2 as nontunable.

```
in(2).MembershipFunctions(1) = setTunable(in(2).MembershipFunctions(1),0);
```

You can also specify the tunability of a subset of variables or rules. For example, set the first two rules as nontunable.

```
rule(1:2) = setTunable(rule(1:2),0);
```

Input Arguments

fis — Fuzzy inference system

mamfis object | sugfis object | mamfistype2 object | sugfistype2 object | fistree object

Fuzzy inference system, specified as a `mamfis`, `sugfis`, `mamfistype2`, `sugfistype2`, or `fistree` object. The fuzzy system can be a fuzzy inference system or network of interconnected fuzzy inference systems.

Output Arguments

in — Tunable settings of input variables

array of `VariableSettings` objects

Tunable settings for input variables, returned as an array of `VariableSettings` objects. Each `VariableSettings` object contains tunability settings for the input variable indicated by its `FISName` and `VariableName` properties.

Specify the tunability settings of the membership functions for this variable, using its `MembershipFunctions` property.

out — Tunable settings of output variables

array of `VariableSettings` objects

Tunable settings for input variables, returned as an array of `VariableSettings` objects. Each `VariableSettings` object contains tunability settings for the output variable indicated by its `FISName` and `VariableName` properties.

Specify the tunability settings of the membership functions for this variable, using its `MembershipFunctions` property.

rule — Tunable settings of rules

array of `RuleSettings` objects

Tunable settings for rules, returned as an array of `RuleSettings` object. Each `RuleSettings` object contain tunability settings for a rule from the FIS indicated by its `FISName` property.

Specify the tunability settings of the antecedent and consequent for this variable, using its `Antecedent` and `Consequent` properties, respectively.

See Also

`setTunable` | `getTunableValues` | `setTunableValues` | `tunefis` | `VariableSettings` | `RuleSettings`

Introduced in R2019a

getTunableValues

Obtain values of tunable parameters from fuzzy inference system

Syntax

```
paramvals = getTunableValues(fis,paramset)
```

Description

`paramvals = getTunableValues(fis,paramset)` returns tunable parameter values of the fuzzy inference system `fis`. To specify the parameter values to return, use `paramset`.

Examples

Obtain Values of Tunable Parameters from FIS

Create a fuzzy inference system, and define the tunable parameter settings of inputs, outputs, and rules.

```
fis = mamfis('NumInputs',2,'NumOutputs',1);  
[in,out,rule] = getTunableSettings(fis);
```

Obtain tunable parameter values of the inputs, outputs, and rules of the fuzzy inference system.

```
paramVals = getTunableValues(fis,[in;out;rule]);
```

Input Arguments

fis — Fuzzy inference system

`mamfis` object | `sugfis` object | `mamfistype2` object | `sugfistype2` object | `fistree` object

Fuzzy inference system, specified as a `mamfis`, `sugfis`, `mamfistype2`, `sugfistype2`, or `fistree` object.

paramset — Tunable parameter settings

array

Tunable parameter settings, specified as an array of input, output, and rule parameter settings in the input FIS. To obtain these parameter settings, use the `getTunableSettings` function with the input `fis`.

`paramset` can be the input, output, or rule parameter settings, or any combination of these settings.

Output Arguments

paramvals — Tunable parameter values

array

Tunable parameter values, returned as an array. The order of the values in `paramvals` matches the order of the parameters in `paramset`.

You can modify these parameter values, and then set them in your FIS using `setTunableValues`.

See Also

`mamfis` | `sugfis` | `mamfistype2` | `sugfistype2` | `getTunableSettings` | `tunefis` | `setTunableValues`

Introduced in R2019a

linsmf

Linear s-shaped saturation membership function

Syntax

```
y = linsmf(x,params)
```

Description

This function computes fuzzy membership values using a linear s-shaped membership function. You can also compute this membership function using a `fismf` object. For more information, see “`fismf` Object” on page 8-255.

This membership function is related to the `trimf`, `trapmf`, and `linzmf` membership functions.

`y = linsmf(x,params)` returns fuzzy membership values computed using a linear s-shaped saturation membership function.

- When $a < b$:

$$f(x; a, b) = \begin{cases} 0, & x < a \\ \frac{x-a}{b-a}, & a \leq x \leq b \\ 1, & x > b \end{cases}$$

- When $a = b$:

$$f(x; a, b) = \begin{cases} 0, & x < a \\ 1, & x \geq a \end{cases}$$

To define the membership function parameters, specify `params` as the vector $[a \ b]$.

Membership values are computed for each input value in `x`.

Examples

Linear S-Shaped Membership Function

Specify input values across the universe of discourse.

```
x = 0:0.1:10;
```

Evaluate a linear s-shaped membership function for the input values.


```
y = linsmf(x,[4 6]);
```

Plot the membership function.

```
plot(x,y)
xlabel('linsmf, P = [4 6]')
```



```
ylabel('Membership')
ylim([-0.05 1.05])
```



Input Arguments

x — Input values

scalar | vector

Input values for which to compute membership values, specified as a scalar or vector.

params — Membership function parameters

vector of length two

Membership function parameters, specified as the vector $[a \ b]$. Parameter a defines the *foot* of the membership function, and b defines its *shoulder*. Setting a equal to b produces a crisp membership function.

Output Arguments

y — Membership value

scalar | vector

Membership value, returned as a scalar or a vector. The dimensions of y match the dimensions of x . Each element of y is the membership value computed for the corresponding element of x .

Alternative Functionality

fismf Object

You can create and evaluate a `fismf` object that implements the `linsmf` membership function.

```
mf = fismf("linsmf",P);  
Y = evalmf(mf,X);
```

Here, `X`, `P`, and `Y` correspond to the `x`, `params`, and `y` arguments of `linsmf`, respectively.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using MATLAB® Coder™.

See Also

`fismf` | `fismftype2` | `psigmf` | `sigmf` | `gaussmf` | `gauss2mf` | `gbellmf` | `trimf` | `trapmf` | `linzmf` | `pimf` | `smf` | `zmf` | `dsigmf`

Topics

“Membership Functions” on page 1-9

Introduced in R2022a

linzmf

Linear z-shaped saturation membership function

Syntax

```
y = linzmf(x,params)
```

Description

This function computes fuzzy membership values using a linear z-shaped membership function. You can also compute this membership function using a `fismf` object. For more information, see “`fismf` Object” on page 8-255.

This membership function is related to the `trimf`, `trapmf`, and `linsmf` membership functions.

`y = linzmf(x,params)` returns fuzzy membership values computed using a linear z-shaped saturation membership function.

- When $a < b$:

$$f(x; a, b) = \begin{cases} 1, & x < a \\ \frac{a-x}{a-b}, & a \leq x \leq b \\ 0, & x > b \end{cases}$$

- When $a = b$:

$$f(x; a, b) = \begin{cases} 1, & x < a \\ 0, & x \geq a \end{cases}$$

To define the membership function parameters, specify `params` as the vector $[a \ b]$.

Membership values are computed for each input value in `x`.

Examples

Linear Z-Shaped Membership Function

Specify input values across the universe of discourse.

```
x = 0:0.1:10;
```


Evaluate a linear z-shaped membership function for the input values.

```
y = linzmf(x,[4 6]);
```

Plot the membership function.

```
plot(x,y)
xlabel('linzmf, P = [4 6]')
```

```
ylabel('Membership')  
ylim([-0.05 1.05])
```



Input Arguments

x — Input values

scalar | vector

Input values for which to compute membership values, specified as a scalar or vector.

params — Membership function parameters

vector of length two

Membership function parameters, specified as the vector $[a\ b]$. Parameter a defines the *shoulder* of the membership function, and b defines its *foot*. Setting a equal to b produces a crisp membership function.

Output Arguments

y — Membership value

scalar | vector

Membership value, returned as a scalar or a vector. The dimensions of y match the dimensions of x . Each element of y is the membership value computed for the corresponding element of x .

Alternative Functionality

fismf Object

You can create and evaluate a `fismf` object that implements the `linsmf` membership function.

```
mf = fismf("linzmf",P);  
Y = evalmf(mf,X);
```

Here, `X`, `P`, and `Y` correspond to the `x`, `params`, and `y` arguments of `linzmf`, respectively.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using MATLAB® Coder™.

See Also

`fismf` | `fismftype2` | `psigmf` | `sigmf` | `gaussmf` | `gauss2mf` | `gbellmf` | `trimf` | `trapmf` | `linsmf` | `pimf` | `smf` | `zmf` | `dsigmf`

Topics

“Membership Functions” on page 1-9

Introduced in R2022a

mam2sug

(To be removed) Transform Mamdani fuzzy inference system into Sugeno fuzzy inference system

Note mam2sug will be removed in a future release. Use `convertToSugeno` instead. For more information, see “Compatibility Considerations”.

Syntax

```
sugFIS = mam2sug(mamFIS)
```

Description

sugFIS = mam2sug(mamFIS) transforms a Mamdani fuzzy inference system into a Sugeno fuzzy inference system.

Examples

Transform Mamdani FIS into Sugeno FIS

Load a Mamdani fuzzy inference system.


```
mam_fismat = readfis('mam22.fis');
```

Convert this system to a Sugeno fuzzy inference system.

```
sug_fismat = mam2sug(mam_fismat);
```

Plot the output surfaces for both fuzzy systems.

```
subplot(2,2,1)
gensurf(mam_fismat)
title('Mamdani system (Output 1)')
subplot(2,2,2)
gensurf(sug_fismat)
title('Sugeno system (Output 1)')
subplot(2,2,3)
gensurf(mam_fismat,gensurfOptions('OutputIndex',2))
title('Mamdani system (Output 2)')
subplot(2,2,4)
gensurf(sug_fismat,gensurfOptions('OutputIndex',2))
title('Sugeno system (Output 2)')
```



The output surfaces for both systems are similar.

Input Arguments

mamFIS — Mamdani fuzzy inference system

structure

Mamdani fuzzy inference system, specified as a structure. Construct mamFIS at the command line or using the Fuzzy Logic Designer. For more information, see “Build Fuzzy Systems at the Command Line” on page 2-31 and “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14.

Output Arguments

sugFIS — Sugeno fuzzy inference system

structure

Sugeno fuzzy inference system, returned as a structure. sugFIS:

- Has constant output membership functions, whose values correspond to the centroids of the output membership functions in mamFIS
- Uses the weighted-average defuzzification method
- Uses the product implication method
- Uses the sum aggregation method

The remaining properties of `sugFIS`, including the input membership functions and rule definitions remain unchanged from `mamFIS`.

Tips

- If you have a functioning Mamdani fuzzy inference system, consider using `mam2sug` to convert to a more computationally efficient Sugeno structure to improve performance.
- If `sugFIS` has a single output variable and you have appropriate measured input/output training data, you can tune the membership function parameters of `sugFIS` using `anfis`.

Compatibility Considerations

`mam2sug` will be removed

Not recommended starting in R2018b

`mam2sug` will be removed in a future release. Use `convertToSugeno` instead. To update your code, change the function name from `mam2sug` to `convertToSugeno`. The syntaxes are equivalent.

See Also

`convertToSugeno` | **Fuzzy Logic Designer**

Topics

“Mamdani and Sugeno Fuzzy Inference Systems” on page 2-2

“Build Fuzzy Systems at the Command Line” on page 2-31

“Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14

Introduced before R2006a

mf2mf

(To be removed) Translate parameters between membership functions

Note mf2mf will be removed in a future release. Convert membership functions using dot notation on `fismf` objects instead. For more information, see “Compatibility Considerations”.

Syntax

```
outParams = mf2mf(inParams,inType,outType)
```

Description

`outParams = mf2mf(inParams,inType,outType)` converts the parameters for one type of membership function into those of another membership function.


Occasionally this translation results in lost information, so that if the output parameters are translated back into the original membership function type, the transformed membership function does not look the same as the original function.

Examples

Translate Parameters Between Membership Functions

Create parameters for a generalized bell-shaped membership function, then convert them to parameters for a triangular membership function. Plot both functions to compare.

```
x = 0:0.1:5;  
mf1 = [1 2 3];  
mf2 = mf2mf(mf1,'gbellmf','trimf');  
plot(x,gbellmf(x,mf1),x,trimf(x,mf2))  
legend('Generalized bell-shaped','Triangle-shaped','Location','South')  
ylim([-0.05 1.05])
```



Input Arguments

inParams — Initial membership function parameters

vector

Initial membership function parameters, specified as a vector.

inType — Initial membership function type

character vector | string

Initial membership function type, specified as one of the following membership functions.

Membership function type	Description	For more information
'gbellmf'	Generalized bell-shaped membership function	gbellmf
'gaussmf'	Gaussian membership function	gaussmf
'gauss2mf'	Gaussian combination membership function	gauss2mf
'trimf'	Triangular membership function	trimf
'trapmf'	Trapezoidal membership function	trapmf
'sigmf'	Sigmoidal membership function	sigmf

Membership function type	Description	For more information
'dsigmf'	Difference between two sigmoidal membership functions	dsigmf
'psigmf'	Product of two sigmoidal membership functions	psigmf
'zmf'	Z-shaped membership function	zmf
'pimf'	Pi-shaped membership function	pimf
'smf'	S-shaped membership function	smf

outType — Final membership function type

character vector | string

Final membership function type, specified as one of the following membership functions.

Membership function type	Description	For more information
'gbellmf'	Generalized bell-shaped membership function	gbellmf
'gaussmf'	Gaussian membership function	gaussmf
'gauss2mf'	Gaussian combination membership function	gauss2mf
'trimf'	Triangular membership function	trimf
'trapmf'	Trapezoidal membership function	trapmf
'sigmf'	Sigmoidal membership function	sigmf
'dsigmf'	Difference between two sigmoidal membership functions	dsigmf
'psigmf'	Product of two sigmoidal membership functions	psigmf
'zmf'	Z-shaped membership function	zmf
'pimf'	Pi-shaped membership function	pimf
'smf'	S-shaped membership function	smf

Output Arguments

outParams — Final membership function parameters

vector

Final membership function parameters, returned as a vector.

Compatibility Considerations

mf2mf will be removed

Not recommended starting in R2018b

mf2mf will be removed in a future release. Convert membership functions using dot notation on fismf objects instead. There are differences between these approaches that require updates to your code.

Update Code

Previously, to change the type of a membership function in a fuzzy inference system, you converted the parameters using mf2mf.

```
fis = readfis('tipper');  
oldType = fis.input(1).mf(1).type;  
oldParams = fis.input(1).mf(1).params;  
fis.input(1).mf(1).type = newType;  
fis.input(1).mf(1).params = mf2mf(oldParams,oldType,newType);
```

Now, when you change the type of membership function, the parameters are converted automatically.

```
fis = readfis('tipper');  
fis.Inputs(1).MembershipFunctions(1).Type = newType;
```

Previously, membership functions were represented as structures within a fuzzy inference system structure. Now, membership functions are represented as fismf objects within mamfis and sugfis objects. For more information on fuzzy inference system objects, see mamfis and sugfis.

See Also

evalmf | gaussmf | gauss2mf | gbellmf | trimf | trapmf | pimf | smf | zmf | psigmf | sigmf | dsigmf | trimf | trapmf

Topics

“Membership Functions” on page 1-9

“The Membership Function Editor” on page 2-20

Introduced before R2006a

mfedit

Open Membership Function Editor

Syntax

```
mfedit
mfedit(fis)
mfedit(fileName)
```

Description

Using the Membership Function Editor, you specify the range of each input and output variables. Then, for each variable, you define the number of membership functions, the type of each membership function, and the membership function parameters.

The **Fuzzy Logic Designer** app consists of several interactive interfaces for creating a fuzzy inference system (FIS), including the Membership Function Editor. For more information on interactively creating fuzzy systems, see “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14.

`mfedit` opens the Membership Function Editor with no fuzzy inference system loaded.

`mfedit(fis)` opens the Membership Function Editor and loads the fuzzy inference system `fis`.

`mfedit(fileName)` opens the Membership Function Editor and loads a fuzzy inference system from the file specified by `fileName`.

Examples


Open Membership Function Editor

Load or create a fuzzy inference system object. For this example, load the fuzzy system from a file.

```
fis = readfis('tipper');
```

Open the Membership Function Editor for this fuzzy system.

```
mfedit(fis)
```



Input Arguments

fis – Fuzzy inference system

mamfis object | sugfis object

Fuzzy inference system, specified as either a mamfis or sugfis object in the MATLAB workspace.

fileName – File name

string | character vector

File name specified as a string or character vector with or without the `.fis` extension. This file must be in the current working directory or on the MATLAB path.

Compatibility Considerations

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

See Also

Apps

Fuzzy Logic Designer

Functions

`ruleedit` | `ruleview` | `surfview` | `addMF` | `plotmf`

Topics

“Membership Functions” on page 1-9

“The Membership Function Editor” on page 2-20

Introduced before R2006a

newfis

(To be removed) Create new fuzzy inference system

Note newfis will be removed in a future release. Use mamfis or sugfis instead. For more information, see “Compatibility Considerations”.

Syntax

```
fis = newfis(name)
fis = newfis(name,Name,Value)
```

Description

fis = newfis(name) returns a default Mamdani fuzzy inference system with the specified name.

fis = newfis(name,Name,Value) returns a fuzzy inference system with properties specified using one or more Name,Value pair arguments.

Examples

Create Fuzzy Inference System

Create a default Mamdani fuzzy inference system with the name, 'fis'.

```
sys = newfis('fis')

sys = struct with fields:
    name: 'fis'
    type: 'mamdani'
    andMethod: 'min'
    orMethod: 'max'
    defuzzMethod: 'centroid'
    impMethod: 'min'
    aggMethod: 'max'
    input: []
    output: []
    rule: []
```

Create Sugeno Fuzzy Inference System

Create a default Sugeno fuzzy inference system with the name, 'fis'.

```
sys = newfis('fis','FISType','sugeno')

sys = struct with fields:
    name: 'fis'
    type: 'sugeno'
```



```

    andMethod: 'prod'
    orMethod: 'probor'
    defuzzMethod: 'wtaver'
    impMethod: 'prod'
    aggMethod: 'sum'
    input: []
    output: []
    rule: []

```

Specify Implication Methods for New Fuzzy Inference System

Create a Mamdani fuzzy inference system that uses 'bisector' defuzzification and 'prod' implication.

```

sys = newfis('fis','DefuzzificationMethod','bisector',...
            'ImplicationMethod','prod');

```

Input Arguments

name — Fuzzy inference system name

character vector | string

Fuzzy inference system name, specified as a character vector or string.

Name-Value Pair Arguments

Specify optional pairs of arguments as Name1=Value1,...,NameN=ValueN, where Name is the argument name and Value is the corresponding value. Name-value arguments must appear after other arguments, but the order of the pairs does not matter.

Before R2021a, use commas to separate each name and value, and enclose Name in quotes.

Example: 'OrMethod','probor' configures the fuzzy OR operator as a probabilistic OR function.

FISType — Fuzzy inference system type

'mamdani' (default) | 'sugeno'

Fuzzy inference system type, specified as one of the following:

- 'mamdani' — Mamdani-type fuzzy system
- 'sugeno' — Sugeno-type fuzzy system

For more information on the types of fuzzy inference systems, see “Mamdani and Sugeno Fuzzy Inference Systems” on page 2-2.

AndMethod — AND fuzzy operator method

'min' | 'prod' | character vector | string

AND fuzzy operator method, specified as one of the following:

- 'min' — Minimum of fuzzified input values. This method is the default when FISType is 'mamdani'.

- 'prod' — Product of fuzzified input values. This method is the default when FISType is 'sugeno'.
- Character vector or string — Name of a custom AND function in the current working folder or on the MATLAB path. For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on fuzzy operators and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

OrMethod — OR fuzzy operator method

'max' | 'probor' | character vector | string

OR fuzzy operator method, specified as one of the following:

- 'max' — Maximum of fuzzified input values. This method is the default when FISType is 'mamdani'.
- 'probor' — Probabilistic OR of fuzzified input values. For more information, see `probor`. This method is the default when FISType is 'sugeno'.
- Character vector or string — Name of a custom OR function in the current working folder or on the MATLAB path. For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on fuzzy operators and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

ImplicationMethod — Implication method

'min' | 'prod' | character vector | string

Implication method for computing consequent fuzzy set, specified as one of the following:

- 'min' — Truncate the consequent membership function at the antecedent result value. This method is the default when FISType is 'mamdani'.
- 'prod' — Scale the consequent membership function by the antecedent result value. This method is the default when FISType is 'sugeno'.
- Character vector or string — Name of a custom implication function in the current working folder or on the MATLAB path. For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

Note No matter what implication method you specify, Sugeno systems always use 'prod' aggregation.

For more information on implication and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

AggregationMethod — Aggregation method

'max' | 'sum' | character vector | string

Aggregation method for combining rule consequents, specified as one of the following:

- 'max' — Maximum of consequent fuzzy sets. This method is the default when FISType is 'mamdani'.

- 'sum' — Sum of consequent fuzzy sets. This method is the default when `FISType` is 'sugeno'.
- 'probor' — Probabilistic OR of consequent fuzzy sets. For more information, see `probor`.
- Character vector or string — Name of a custom aggregation function in the current working folder or on the MATLAB path. For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

Note No matter what aggregation method you specify, Sugeno systems always use 'sum' aggregation.

For more information on aggregation and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

DefuzzificationMethod — Defuzzification method

'centroid' | 'bisector' | 'mom' | 'lom' | 'som' | 'wtaver' | 'wtsum' | character vector | string

Defuzzification method for computing crisp output values.

If `FISType` is 'mamdani', specify the defuzzification method as one of the following:

- 'centroid' — Centroid of the area under the output fuzzy set. This method is the default for Mamdani systems.
- 'bisector' — Bisector of the area under the output fuzzy set
- 'mom' — Mean of the values for which the output fuzzy set is maximum
- 'lom' — Largest value for which the output fuzzy set is maximum
- 'som' — Smallest value for which the output fuzzy set is maximum

If `FISType` is 'sugeno', specify the defuzzification method as one of the following:

- 'wtaver' — Weighted average of all rule outputs. This method is the default for Sugeno systems.
- 'wtsum' — Weighted sum of all rule outputs

You can also specify the defuzzification method using a character vector or string that contains the name of a custom function in the current working folder or on the MATLAB path. For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on defuzzification and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

Output Arguments

fis — Fuzzy inference system

FIS structure

Fuzzy inference system with the specified `name`, returned as an FIS structure. The fuzzy system is configured using the specified `Name`, `Value` pair arguments.

`fis` has no input variables, output variables, or rules. To add variables or rules to `fis`, use `addvar` or `addRule`. You can also edit the fuzzy system using **Fuzzy Logic Designer**.

Compatibility Considerations

newfis will be removed

Not recommended starting in R2018b

`newfis` will be removed in a future release. Use `mamfis` or `sugfis` instead. There are differences between these functions that require updates to your code.

To create a Mamdani or Sugeno FIS, use `mamfis` or `sugfis`, respectively.

Update Code

This table shows some typical usages of `newfis` for creating fuzzy systems and how to update your code to use `mamfis` or `sugfis` instead.

If your code has this form:	Use this code instead:
<code>fis = newfis(name)</code>	<code>fis = mamfis('Name',name)</code>
<code>fis = newfis(name,'FISType','mamdani')</code>	<code>fis = mamfis('Name',name)</code>
<code>fis = newfis(name,'FISType','sugeno')</code>	<code>fis = sugfis('Name',name)</code>
<code>fis = newfis(name,... 'FISType','mamdani',... 'AndMethod','prod')</code>	<code>fis = mamfis('Name',name,... 'AndMethod','prod')</code>
<code>fis = newfis(name,... 'FISType','sugeno',... 'OrMethod','probor')</code>	<code>fis = sugfis('Name',name,... 'OrMethod','probor')</code>

See Also

`mamfis` | `sugfis` | `readfis` | `writeFIS`

Topics

“Foundations of Fuzzy Logic” on page 1-7

“Fuzzy Inference Process” on page 1-19

Introduced before R2006a

parsrule

(To be removed) Parse fuzzy rules

Note `parsrule` will be removed in a future release. Use `addRule` instead. For more information, see “Compatibility Considerations”.

Syntax

```
outFIS = parsrule(inFIS,ruleList)
outFIS = parsrule(inFIS,ruleList,Name,Value)
```

Description

`outFIS = parsrule(inFIS,ruleList)` returns a fuzzy inference system, `outFIS`, that is equivalent to the input fuzzy system, `inFIS`. but with fuzzy rules replaced by the rules specified in `ruleList`.

`outFIS = parsrule(inFIS,ruleList,Name,Value)` parses the rules in `ruleList` using options specified by one or more `Name,Value` pair arguments.

Examples

Add Rules to Fuzzy Inference System

Load a fuzzy inference system (FIS).

```
fis = readfis('tipper');
```

Specify if-then rules using the default 'verbose' format.

```
rule1 = "If service is poor or food is rancid then tip is cheap";
rule2 = "If service is excellent and food is not rancid then tip is generous";
rules = [rule1 rule2];
```

Add the rules to the FIS.

```
fis2 = parsrule(fis,rules);
```

`fis2` is equivalent to `fis`, except that the rule base is replaced with the specified rules.

Add Rules Using Symbolic Expressions

Load a fuzzy inference system (FIS).

```
fis = readfis('tipper');
```

Specify the following rules using symbols:

- If service is poor or food is rancid then tip is cheap.
- If service is excellent and food is not rancid then tip is generous.

```
rule1 = "service==poor | food==rancid => tip=cheap";
rule2 = "service==excellent & food~=rancid => tip=generous";
rules = [rule1 rule2];
```

Add the rules to the FIS using the 'symbolic' format.

```
fis2 = parsrule(fis,rules,'Format','symbolic');
```

Add Rules Using Membership Function Indices

Load fuzzy inference system (FIS).

```
fis = readfis('mam22.fis');
```

Specify the following rules using membership function indices:

- If angle is small and velocity is big, then force is negBig and force2 is posBig2.
- If angle is not small and velocity is small, then force is posSmall and force2 is negSmall2.

```
rule1 = "1 2, 1 4 (1) : 1";
rule2 = "-1 1, 3 2 (1) : 1";
rules = [rule1 rule2];
```

Add rules to FIS using the 'indexed' format.

```
fis2 = parsrule(fis,rules,'Format','indexed');
```

Add Rules Using French Language

Load a fuzzy inference system (FIS).

```
fis = readfis('tipper');
```

Specify if-then rules using French keywords.

```
rule1 = "Si service est poor ou food est rancid alors tip est cheap";
rule2 = "Si service est excellent et food n'est_pas rancid alors tip est generous";
rules = [rule1 rule2];
```

Add the rules to the FIS.

```
fis2 = parsrule(fis,rules,'Language','français');
```

Add Single Rule to Fuzzy Inference System

Load a fuzzy inference system (FIS).

```
a = readfis('tipper');
```

Add a rule to the FIS.

```
ruleTxt = 'If service is poor then tip is cheap';
a2 = parsrule(a,ruleTxt,'verbose');
```

Input Arguments

inFIS — Fuzzy inference system

FIS structure

Input fuzzy inference system, specified as an FIS structure. `parsrule` does not modify `inFIS`.

ruleList — Fuzzy rules

character array | string array | character vector | string

Fuzzy rules, specified as one of the following:

- Character array where each row corresponds to a rule. For example:

```
rule1 = 'If service is poor or food is rancid then tip is cheap';
rule2 = 'If service is good then tip is average';
rule3 = 'If service is excellent or food is delicious then tip is generous';
ruleList = char(rule1,rule2,rule3);
```

- String array, where each element corresponds to a rule. For example:

```
ruleList = ["If service is poor or food is rancid then tip is cheap";
            "If service is good then tip is average";
            "If service is excellent or food is delicious then tip is generous"];
```

- Character vector or string to specify a single rule.

You can change the rule format and language using the `Format` and `Language` options.

Name-Value Pair Arguments

Specify optional pairs of arguments as `Name1=Value1, ..., NameN=ValueN`, where `Name` is the argument name and `Value` is the corresponding value. Name-value arguments must appear after other arguments, but the order of the pairs does not matter.

Before R2021a, use commas to separate each name and value, and enclose Name in quotes.

Example: `'Format','symbolic'` sets the rule format to symbolic expressions.

Format — Rule format

'verbose' (default) | 'symbolic' | 'indexed'

Rule format, specified as the comma-separated pair consisting 'Format' and one of the following:

- 'verbose' — Use linguistic expressions.

```
'If service is poor or food is rancid then tip is cheap 1'
```

Specify the rule weight at the end of the rule text. If you omit the weight, a default value of 1 is used.

You can specify the rule language using the `Language` option.

- 'symbolic' — Use language-neutral symbolic expressions.

```
'service==poor | food==rancid => tip=cheap 1'
```

Specify symbolic expressions using the following symbols.

Rule Component	Symbol
AND	&
OR	
IS (in antecedent)	==
IS (in consequent)	=
IS NOT	~=
Implication (then)	=>

Specify the rule weight at the end of the rule text. If you omit the weight, a default value of 1 is used.

- 'indexed' — Use input and output membership function (MF) indices.

Specify indexed rules in the following format:

```
'<input MFs>, <output MFs>, (<weight>) : <logical operator - 1(AND), 2(OR)>'
```

For example:

```
'1 1, 1 (1) : 2'
```

To indicate NOT operations for input and output membership functions, use negative indices. For example, to specify “not the second membership function,” use -2.

To indicate a don't care condition for an input or output membership function, use 0.

Language — Rule language

```
'english' (default) | 'français' | 'deutsch'
```

Rule language for 'verbose' format, specified as one of the following:

- 'english' — Specify rules in English.
'If service is poor or food is rancid then tip is cheap'
- 'français' — Specify rules in French.
'Si service est poor ou food est rancid alors tip est cheap'
- 'deutsch' — Specify rules in German.
'Wenn service ist poor oder food ist rancid dann tip ist cheap'

The software parses the rules in ruleList using the following keywords.

Rule Component	English	French	German
Start of antecedent	if	si	wenn
AND	and	et	und
OR	or	ou	oder
Start of consequent (implication)	then	alors	dann

Rule Component	English	French	German
IS	is	est	ist
IS NOT	is not	n' 'est_pas	ist nicht

Output Arguments

outFIS — Output fuzzy inference system

FIS structure

Fuzzy inference system, returned as an FIS structure. outFIS is the same as inFIS, except that the rule list contains only the rules specified in ruleList.

Compatibility Considerations

parsrule will be removed

Not recommended starting in R2018b

parsrule will be removed in a future release. Use addRule instead.

Update Code

If you previously added rules using linguistic or symbolic expressions with parsrule, you can specify rules using the same expressions with addRule. addRule automatically detects the format of the strings or character vectors in your rule list. Therefore, it is no longer necessary to specify the rule format. To add a rule list using addRule, use the following command:

```
fis = addRule(fis,rules);
```

Previously, you could add rules using indexed expressions with parsrule.

```
rule1 = "1 2, 1 4 (1) : 1";
rule2 = "-1 1, 3 2 (1) : 1";
rules = [rule1 rule2];
fis = parsrule(fis,rules,'Format','indexed');
```

Now, specify these rules using arrays of indices.

```
rule1 = [1 2 1 4 1 1];
rule2 = [-1 1 3 2 1 1];
rules = [rule1; rule2];
fis = addRule(fis,rules);
```

If you previously specified rules using the 'Language' name-value pair argument with parsrule, this functionality has been removed and there is no replacement. Specify your rules using addRule a different rule format.

Previously, parsrule replaced the entire rule list in your fuzzy system. addRule appends your specified rules to the rule list.

See Also

[addRule](#) | [ruleedit](#) | [showrule](#)

Introduced before R2006a

pimf

Pi-shaped membership function

Syntax

```
y = pimf(x,params)
```

Description

This function computes fuzzy membership values using a spline-based pi-shaped membership function. You can also compute this membership function using a `fismf` object. For more information, see “`fismf` Object” on page 8-177.

This membership function is related to the `smf` and `zmf` membership functions.

`y = pimf(x,params)` returns fuzzy membership values computed using a spline-based pi-shaped membership function. This membership function is the product of an `smf` function and a `zmf` function, and is given by:

$$f(x; a, b, c, d) = \left\{ \begin{array}{ll} 0, & x \leq a \\ 2\left(\frac{x-a}{b-a}\right)^2, & a \leq x \leq \frac{a+b}{2} \\ 1-2\left(\frac{x-b}{b-a}\right)^2, & \frac{a+b}{2} \leq x \leq b \\ 1, & b \leq x \leq c \\ 1-2\left(\frac{x-c}{d-c}\right)^2, & c \leq x \leq \frac{c+d}{2} \\ 2\left(\frac{x-d}{d-c}\right)^2, & \frac{c+d}{2} \leq x \leq d \\ 0, & x \geq d \end{array} \right.$$

To define the membership function parameters, specify `params` as the vector `[a b c d]`.

Membership values are computed for each input value in `x`.

Examples

Pi-Shaped Membership Function

Specify input values across the universe of discourse.


```
x = 0:0.1:10;
```

Evaluate membership function for the input values.

```
y = pimf(x,[1 4 5 10]);
```

Plot the membership function.

```
plot(x,y)
title('pimf, P = [1 4 5 10]')
xlabel('x')
ylabel('Degree of Membership')
ylim([-0.05 1.05])
```



Input Arguments

x — Input values

scalar | vector

Input values for which to compute membership values, specified as a scalar or vector.

params — Membership function parameters

vector of length two

Membership function parameters, specified as the vector $[a \ b \ c \ d]$. Parameters a and d define the *feet* of the membership function, and b and c define its *shoulders*.

Output Arguments

y — Membership value

scalar | vector

Membership value returned as a scalar or a vector. The dimensions of `y` match the dimensions of `x`. Each element of `y` is the membership value computed for the corresponding element of `x`.

Alternative Functionality

fismf Object

You can create and evaluate a `fismf` object that implements the `pimf` membership function.

```
mf = fismf("pimf",P);  
Y = evalmf(mf,X);
```

Here, `X`, `P`, and `Y` correspond to the `x`, `params`, and `y` arguments of `pimf`, respectively.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using MATLAB® Coder™.

See Also

`fismf` | `fismftype2` | `psigmf` | `sigmf` | `gaussmf` | `gauss2mf` | `gbellmf` | `trimf` | `trapmf` | `linsmf` | `linzmf` | `smf` | `zmf` | `dsigmf`

Topics

"Membership Functions" on page 1-9

Introduced before R2006a

plotfis

Display fuzzy inference system

Syntax

```
plotfis(fis)

plotfis(tree)
plotfis(tree, Legend="on")
```

Description

FIS Object

`plotfis(fis)` displays a high-level diagram of a type-1 or type-2 fuzzy inference system (FIS). The center of the display shows the name, type, and rule count for the FIS. The input variables with their associated membership functions are displayed on the left, and the outputs with their associated membership functions are displayed on the right.

FIS Tree

`plotfis(tree)` displays a high-level diagram of a tree of interconnected FIS objects. The display shows the inputs, outputs, component FIS objects, and connections of the specified `fistree` object.

`plotfis(tree, Legend="on")` displays information about the inputs, outputs, and connections of the specified `fistree` object by adding a legend to the display.

Examples


Display Fuzzy Inference System

Create a fuzzy inference system (FIS). For this example, read the FIS from the `tipper.fis` file.

```
fis = readfis('tipper');
```

Display the fuzzy system.

```
plotfis(fis)
```



System tipper: 2 inputs, 1 outputs, 3 rules

The figure shows the FIS name and type, along with the number of rules. Also, for each input and output variable, the name and membership function configuration are shown.

Display Tree of Fuzzy Inference Systems

Create a `fistree` object from three fuzzy inference systems and their connections.

```


fis1 = mamfis('Name','fis1','NumInputs',2,'NumOutputs',1);
fis2 = sugfis('Name','fis2','NumInputs',2,'NumOutputs',2);
fis3 = sugfis('Name','fis3','NumInputs',3,'NumOutputs',1);
con1 = ["fis1/output1" "fis3/input1"];
con2 = ["fis2/output1" "fis3/input2"];
con3 = ["fis1/input2" "fis2/input1"];

```

```
tree = fistree([fis1 fis2 fis3],[con1; con2; con3]);
```

Display the `fistree` object with a legend.


```
plotfis(tree,Legend="on")
```



In this display, free inputs are the inputs without any incoming connections. You must specify these inputs when you evaluate the FIS tree. The free and intermediate output values are returned when you evaluate the FIS tree.

You can also plot the FIS tree without a legend.

```
plotfis(tree)
```

Input Arguments

fis – Fuzzy inference system

`mamfis` object | `sugfis` object | `mamfistype2` object | `sugfistype2` object

Fuzzy inference system, specified as one of the following:

- `mamfis` object – Mamdani fuzzy inference system
- `sugfis` object – Sugeno fuzzy inference system
- `mamfistype2` object – Type-2 Mamdani fuzzy inference system
- `sugfistype2` object – Type-2 Sugeno fuzzy inference system

tree – Tree of interconnected fuzzy inference systems

`fistree` object

Tree of interconnected fuzzy inference systems, specified as a `fistree` object.

Compatibility Considerations

plotfis displays a visual representation of a FIS tree

Behavior changed in R2021b

Starting in R2021b, the `plotfis` function displays a visual representation of a FIS tree. Previously, `plotfis` displayed a summary of the FIS tree properties in the MATLAB Command Window. This information is no longer available in the Command Window when using `plotfis`.

To access information about the FIS tree components, inputs, outputs, and connections, access the properties of the `fistree` object using dot notation.

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

See Also

`mamfis` | `sugfis` | `mamfistype2` | `sugfistype2` | `readfis` | `evalmf` | `plotmf` | `fistree`

Topics

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced before R2006a

plotmf

Plot membership functions for input or output variable

Syntax

```
plotmf(fis,variableType,variableIndex)
```

```
plotmf( ____,numPoints)
```

```
[xOut,mfOut] = plotmf( ____)
```

```
[xOut,umfOut,lmfOut] = plotmf( ____)
```

Description

`plotmf(fis,variableType,variableIndex)` plots the membership functions for an input or output variable in the fuzzy inference system `fis`.

`plotmf(____,numPoints)` specifies the number of data points to plot for each membership function.

`[xOut,mfOut] = plotmf(____)` returns the universe of discourse (`xOut`) and membership function (`mfOut`) values without plotting them. Use this syntax when `fis` is a type-1 fuzzy inference system.

`[xOut,umfOut,lmfOut] = plotmf(____)` returns the universe of discourse (`xOut`), upper membership function (`umfOut`), and lower membership function (`lmfOut`) values without plotting them. Use this syntax when `fis` is a type-2 fuzzy inference system.

Examples


Plot Membership Functions for Input Variable

Create a fuzzy inference system.

```
fis = readfis('tipper');
```

Plot the membership functions for the first input variable.

```
plotmf(fis,'input',1)
```




Specify Number of Points for Membership Function Plot

Create a fuzzy inference system.

```
fis = readfis('tipper');
```

Plot the membership functions for the first output variable using 101 data points for each membership function.

```
plotmf(fis, 'output', 1, 101)
```



Obtain Membership Function Plot Data

Create a fuzzy inference system.


```
fis = readfis('tipper');
```

Obtain the x-axis and y-axis data for the membership functions of the second input variable.

```
[xOut,yOut] = plotmf(fis,'input',2);
```

You can then, for example, plot a single membership function using this data.

```
plot(xOut(:,2),yOut(:,2))
xlabel('food')
ylabel('delicious membership')
```




Plot Membership Functions for Type-2 FIS

Create a type-2 fuzzy inference system.

```
fis = mamfistype2('NumInputs',3,'NumOutputs',1);
```

Plot the membership functions for the second input variable.

```
plotmf(fis,'input',1)
```




The type-2 membership functions have a footprint of uncertainty (FOU) between their upper and lower membership functions.

You can also obtain the plotting data without generating a plot.

```
[xOut,umfOut,lmfOut] = plotmf(fis,'input',1);
```

You can then plot individual membership functions or plot the data using your own custom formatting. For example, plot the upper and lower membership functions for only the second membership function of the first input variable.

```
plot(xOut(:,2),umfOut(:,2),'r',xOut(:,2),lmfOut(:,2),'b')
xlabel('input1')
ylabel('delicious membership')
```



Input Arguments

fis — Fuzzy inference system

`mamfis object` | `sugfis object` | `mamfistype2 object` | `sugfistype2 object`

Fuzzy inference system, specified as one of the following:

- `mamfis object` — Mamdani fuzzy inference system
- `sugfis object` — Sugeno fuzzy inference system
- `mamfistype2 object` — Type-2 Mamdani fuzzy inference system
- `sugfistype2 object` — Type-2 Sugeno fuzzy inference system

`plotmf` does not support plotting output membership functions of Sugeno systems.

variableType — Variable type

`'input'` | `'output'`

Variable type, specified as one of the following:

- `'input'` — Input variable
- `'output'` — Output variable

variableIndex — Variable index

positive integer

Variable index, specified as a positive integer. If `variableType` is:

- 'input', then `variableIndex` must be less than or equal to the number of input variables in `fis`
- 'output', then `variableIndex` must be less than or equal to the number of output variables in `fis`

numPoints — Number of data points to plot

181 (default) | positive integer

Number of data points to plot, specified as a positive integer.

Output Arguments

x0Out — Universe of discourse data

array

Universe of discourse data, returned as a `numPoints`-by- N_{MF} array, where N_{MF} is the number of membership functions for the variable specified by `variableType` and `variableIndex`.

mf0Out — Membership function data

array

Membership function data for a type-1 membership function, returned as a `numPoints`-by- N_{MF} array, where N_{MF} is the number of membership functions for the variable specified by `variableType` and `variableIndex`.

umf0Out — Upper membership function data

array

Upper membership function data for a type-2 membership function, returned as a `numPoints`-by- N_{MF} array, where N_{MF} is the number of membership functions for the variable specified by `variableType` and `variableIndex`.

lmf0Out — Lower membership function data

array

Lower membership function data for a type-2 membership function, returned as a `numPoints`-by- N_{MF} array, where N_{MF} is the number of membership functions for the variable specified by `variableType` and `variableIndex`.

Compatibility Considerations

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

See Also

Functions

`evalmf` | `plotfis`

Introduced before R2006a

probor

Probabilistic OR

Syntax

```
y = probor(x)
```

Description

`y = probor(x)` returns the probabilistic OR (also known as the algebraic sum) of the columns in `x`. Within the fuzzy inference process, the `probor` function is used as either a fuzzy operator when evaluating rule antecedents or an aggregation operator when combining the output fuzzy sets from all the rules.

Examples

Compute Probabilistic OR Between Two Membership Functions

Define the universe of discourse (input values) for the membership functions.

```
x = 0:0.1:10;
```

Define two Gaussian membership functions with different means and variances.


```
y1 = gaussmf(x,[0.5 4]);  
y2 = gaussmf(x,[2 7]);
```

Compute the probabilistic OR between these membership functions.

```
y = probor([y1;y2]);
```

Plot the results.

```
plot(x,[y1;y2;y])  
legend('y1','y2','y')  
ylim([-0.05 1.05])  
ylabel('Membership')  
xlabel('Input Value')
```



Input Arguments

x — Fuzzy input values

array | row vector

Fuzzy input values, specified as an array or a row vector.

Output Arguments

y — Probabilistic OR values

row vector

Probabilistic OR values, returned as a row vector with the same number of columns as **x**. Each element of **y** contains the probabilistic OR value for the corresponding column in **x**.

If **x** has one row, then $y = x$.

If $x = [A; B]$, where **A** and **B** are row vectors, then the *i*th element of **y** is the following algebraic sum.

$$y(i) = A(i) + B(i) - A(i)*B(i);$$

If **x** has more than two rows, the probabilistic OR is calculated for the first two rows. Then, the probabilistic OR is computed between the result and the next row. This process repeats for each subsequent row.

```
x = [A;B;C;D]
y(i) = A(i) + B(i) - A(i)*B(i);
y(i) = y(i) + C(i) - y(i)*C(i);
y(i) = y(i) + D(i) - y(i)*D(i);
```

See Also

Topics

"Fuzzy Inference Process" on page 1-19

Introduced before R2006a

psigmf

Product of two sigmoidal membership functions

Syntax

```
y = psigmf(x,params)
```

Description

This function computes fuzzy membership values using the product of two sigmoidal membership functions. You can also compute this membership function using a `fismf` object. For more information, see “`fismf` Object” on page 8-196.

This membership function is related to the `sigmf` and `dsigmf` membership functions.

`y = psigmf(x,params)` returns fuzzy membership values computed using the product of two sigmoidal membership functions. Each sigmoidal function is given by:

$$f(x; a_k, c_k) = \frac{1}{1 + e^{-a_k(x - c_k)}}$$

To define the membership function parameters, specify `params` as the vector $[a_1 \ c_1 \ a_2 \ c_2]$.

Membership values are computed for each input value in `x`.

Examples

Product of Two Sigmoidal Membership Functions

Specify input values across the universe of discourse.


```
x = 0:0.1:10;
```

Evaluate membership function for the input values.

```
y = psigmf(x,[2 3 -5 8]);
```

Plot the membership function.

```
plot(x,y)
title('psigmf, P = [2 3 -5 8]')
xlabel('x')
ylabel('Degree of Membership')
ylim([-0.05 1.05])
```



Input Arguments

x — Input values

scalar | vector

Input values for which to compute membership values, specified as a scalar or vector.

params — Membership function parameters

vector of length four

Membership function parameters, specified as the vector $[a_1 \ c_1 \ a_2 \ c_2]$. Here, a_1 and c_1 are the parameters of the first sigmoidal function, and a_2 and c_2 are the parameters of the second sigmoidal function.

For each sigmoidal function, to open the function to the left or right, specify a negative or positive value for a , respectively. The magnitude of a defines the width of the transition area, and parameter c defines the center of the transition area.

To define a unimodal membership function with a maximum value of 1, specify opposite signs for a_1 and a_2 , and select c values far enough apart to allow for both transition areas to reach 1.

Output Arguments

y — Membership value

scalar | vector

Membership value returned as a scalar or a vector. The dimensions of **y** match the dimensions of **x**. Each element of **y** is the membership value computed for the corresponding element of **x**.

Alternative Functionality

fismf Object

You can create and evaluate a **fismf** object that implements the **psigmf** membership function.

```
mf = fismf("psigmf",P);  
Y = evalmf(mf,X);
```

Here, **X**, **P**, and **Y** correspond to the **x**, **params**, and **y** arguments of **psigmf**, respectively.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using MATLAB® Coder™.

See Also

[fismf](#) | [fismftype2](#) | [psigmf](#) | [sigmf](#) | [gaussmf](#) | [gauss2mf](#) | [gbellmf](#) | [trimf](#) | [trapmf](#) | [linsmf](#) | [linzmf](#) | [pimf](#) | [smf](#) | [zmf](#) | [dsigmf](#)

Topics

"Membership Functions" on page 1-9

Introduced before R2006a

readfis

Load fuzzy inference system from file

Syntax

```
fis = readfis(fileName)
fis = readfis
```

Description

You can load a fuzzy inference system (FIS) from a `.fis` file using the `readfis` function. To save a FIS to a file, use the `writeFIS` function.

Note Do not manually edit the contents of a `.fis` file. Doing so can produce unexpected results when loading the file using a function, such as `readfis` and `getCodeGenerationData`, or an app, such as **Fuzzy Logic Designer**.

`fis = readfis(fileName)` reads a FIS from the file specified by `fileName`.

`fis = readfis` opens a dialog box for selecting and reading a `.fis` file.

Examples

Load Fuzzy Inference System from File

Load the fuzzy system stored in the file `tipper.fis`.

```
fis = readfis('tipper')
```

```
fis =
  mamfis with properties:
        Name: "tipper"
      AndMethod: "min"
      OrMethod: "max"
  ImplicationMethod: "min"
  AggregationMethod: "max"
  DefuzzificationMethod: "centroid"
        Inputs: [1x2 fisvar]
        Outputs: [1x1 fisvar]
        Rules: [1x3 fisrule]
  DisableStructuralChecks: 0
```

See 'getTunableSettings' method for parameter optimization.

Input Arguments

fileName — File name

string | character vector

File name, specified as a string or character vector either with or without the `.fis` extension. This file must be in the current working directory or on the MATLAB path.

Output Arguments

fis — Fuzzy inference system

mamfis object | sugfis object | mamfistype2 object | sugfistype2 object

Fuzzy inference system, returned as one of the following:

- `mamfis` object — Mamdani fuzzy inference system
- `sugfis` object — Sugeno fuzzy inference system
- `mamfistype2` object — Type-2 Mamdani fuzzy inference system
- `sugfistype2` object — Type-2 Sugeno fuzzy inference system

Compatibility Considerations

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

See Also

`writeFIS`

Topics

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced before R2006a

removeInput

Remove input variable from fuzzy inference system

Syntax

```
fisOut = removeInput(fisIn,inputName)
```

Description

`fisOut = removeInput(fisIn,inputName)` removes the input variable with the name `inputName` from fuzzy inference system `fisIn` and returns the resulting fuzzy system in `fisOut`.

Examples

Remove Input Variable from Fuzzy Inference System

Load fuzzy system.

```
fis = readfis("tipper");
```

View the input variables of `fis`.

```
fis.Inputs
```

```
ans =  
1x2 fisvar array with properties:
```

```
    Name  
    Range  
    MembershipFunctions
```

```
Details:
```

	Name	Range	MembershipFunctions
1	"service"	0 10	{1x3 fismf}
2	"food"	0 10	{1x2 fismf}

View the rules of `fis`.

```
fis.Rules
```

```
ans =  
1x3 fisrule array with properties:
```

```
    Description  
    Antecedent  
    Consequent  
    Weight  
    Connection
```

Details:

Description

```

1 "service==poor | food==rancid => tip=cheap (1)"
2 "service==good => tip=average (1)"
3 "service==excellent | food==delicious => tip=generous (1)"

```

Remove the `service` input variable.

```
fis = removeInput(fis,"service");
```

View the updated input variables.

```
fis.Inputs
```

```
ans =
  fisvar with properties:
      Name: "food"
      Range: [0 10]
  MembershipFunctions: [1x2 fismf]
```

View the updated rules.

```
fis.Rules
```

```
ans =
  1x2 fisrule array with properties:
      Description
      Antecedent
      Consequent
      Weight
      Connection
```

Details:

Description

```

1 "food==rancid => tip=cheap (1)"
2 "food==delicious => tip=generous (1)"

```

`service` has been removed from the variables and rules of `fis`.

Input Arguments

fisIn — Fuzzy inference system

`mamfis` object | `sugfis` object | `mamfistype2` object | `sugfistype2` object

Fuzzy inference system, specified as one of the following objects.

- `mamfis` object — Mamdani fuzzy inference system

- `sugfis` object — Sugeno fuzzy inference system
- `mamfistype2` object — Type-2 Mamdani fuzzy inference system
- `sugfistype2` object — Type-2 Sugeno fuzzy inference system

inputName — Input variable name

string | character vector

Input variable name, specified as a string or character vector.

Output Arguments

fisOut — Updated fuzzy inference system

`mamfis` object | `sugfis` object | `mamfistype2` object | `sugfistype2` object

Updated fuzzy inference system, returned as one of the following objects.

- `mamfis` object — Mamdani fuzzy inference system
- `sugfis` object — Sugeno fuzzy inference system
- `mamfistype2` object — Type-2 Mamdani fuzzy inference system
- `sugfistype2` object — Type-2 Sugeno fuzzy inference system

`fisOut` has the same properties as `fisIn` except:

- The input variable with the specified name is removed.
- The specified input variable is removed from any fuzzy rules. If a rule has only the specified input variable in its antecedent, then the entire rule is removed. If a rule has more than one input variable in its antecedent, then the specified input variable is removed from the antecedent.

See Also

`addInput` | `fisvar`

Topics

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced in R2018b

removeMF

Remove membership function from fuzzy variable

Syntax

```

fisOut = removeMF(fisIn,varName,mfName)
fisOut = removeMF(fisIn,varName,mfName,'VariableType',varType)

varOut = removeMF(varIn,varName,mfName)

```

Description

`fisOut = removeMF(fisIn,varName,mfName)` removes the membership function `mfName` from the input or output variable `varName` in the fuzzy inference system `fisIn` and returns the resulting fuzzy system in `fisOut`. To use this syntax, `varName` must be a unique variable name within `fisIn`.

`fisOut = removeMF(fisIn,varName,mfName,'VariableType',varType)` removes the membership function from either an input or output variable as specified by `varType`. Use this syntax when your FIS has an input variable with the same name as an output variable.

`varOut = removeMF(varIn,varName,mfName)` removes the membership function `mfName` from the fuzzy variable `varIn` and returns the resulting fuzzy variable in `varOut`.

Examples

Remove Membership Function from Fuzzy Inference System

Create a Mamdani fuzzy inference system with two inputs and one output. By default, when you specify the number of inputs and outputs, `mamfis` adds three membership functions to each variable.

```

fis = mamfis('NumInputs',3,'NumOutputs',1)

```

```

fis =
    mamfis with properties:
        Name: "fis"
        AndMethod: "min"
        OrMethod: "max"
        ImplicationMethod: "min"
        AggregationMethod: "max"
        DefuzzificationMethod: "centroid"
        Inputs: [1x3 fisvar]
        Outputs: [1x1 fisvar]
        Rules: [1x27 fisrule]
        DisableStructuralChecks: 0

```


See 'getTunableSettings' method for parameter optimization.

Name the variables. For this example, give the second input variable and the output variable the same name.

```
fis.Inputs(1).Name = "speed";  
fis.Inputs(2).Name = "throttle";  
fis.Inputs(3).Name = "distance";  
fis.Outputs(1).Name = "throttle";
```

View the membership functions for the first input variable.

```
plotmf(fis,"input",1)
```




Remove the second membership function, mf2, from the first input variable.

```
fis = removeMF(fis,"speed","mf2");
```

View the membership functions again. The specified membership function has been removed.

```
plotmf(fis,"input",1)
```




If your system has an input variable with the same name as an output variable, you must specify the variable type when removing a membership function. For example, remove the mf3 membership function from the output variable.

```
fis = removeMF(fis,"throttle","mf3",'VariableType',"output");
```

View the membership functions of the output variable.

```
plotmf(fis,"output",1)
```

Remove Membership Function from Fuzzy Variable

Create a fuzzy variable with a specified range and add three membership functions

```
var = fisvar([0 10]);
var = addMF(var, "trimf", [0 2.5 5], "Name", "small");
var = addMF(var, "trimf", [2.5 5 7.5], "Name", "medium");
var = addMF(var, "trimf", [5 7.5 10], "Name", "large");
```

View the membership functions.

```
var.MembershipFunctions
```

```
ans =
  1x3 fismf array with properties:
```

```
Type
Parameters
Name
```

Details:

	Name	Type	Parameters
1	"small"	"trimf"	0 2.5 5

```

2   "medium"   "trimf"   2.5   5   7.5
3   "large"    "trimf"   5     7.5  10

```

Remove the `medium` membership function from the variable.

```
var = removeMF(var,"medium");
```

Verify that the membership was removed.

```
var.MembershipFunctions
```

```
ans =
  1x2 fismf array with properties:
```

```

Type
Parameters
Name

```

Details:

	Name	Type	Parameters		
1	"small"	"trimf"	0	2.5	5
2	"large"	"trimf"	5	7.5	10

Input Arguments

fisIn — Fuzzy inference system

`mamfis` object | `sugfis` object | `mamfistype2` object | `sugfistype2` object

Fuzzy inference system, specified as one of the following objects.

- `mamfis` object — Mamdani fuzzy inference system
- `sugfis` object — Sugeno fuzzy inference system
- `mamfistype2` object — Type-2 Mamdani fuzzy inference system
- `sugfistype2` object — Type-2 Sugeno fuzzy inference system

varName — Variable name

string | character vector

Variable name, specified as a string or character vector. You can specify the name of either an input or output variable in your FIS.

mfName — Membership function name

string | character vector

Membership function name, specified as a string or character vector.

varType — Variable type

string | character vector

Variable type, specified as one of the following:

- "input" — Input variable
- "output" — Output variable

If your system has an input variable with the same name as an output variable, specify which variable to remove the membership function from using `varType`.

varIn — Fuzzy variable

`fisvar` object

Fuzzy variable, specified as a `fisvar` object.

Output Arguments

fisOut — Updated fuzzy inference system

`mamfis` object | `sugfis` object | `mamfistype2` object | `sugfistype2` object

Update fuzzy inference system, returned as one of the following objects.

- `mamfis` object — Mamdani fuzzy inference system
- `sugfis` object — Sugeno fuzzy inference system
- `mamfistype2` object — Type-2 Mamdani fuzzy inference system
- `sugfistype2` object — Type-2 Sugeno fuzzy inference system

`fisOut` has the same properties as `fisIn` except:

- The membership function with the specified name is removed from the specified variable.
- The specified membership function is removed from any fuzzy rules. If a rule has only the specified membership function in its antecedent, then the entire rule is removed. If a rule has more than one membership function in its antecedent, then the specified membership function is removed from the antecedent.

varOut — Fuzzy variable

`fisvar` object

Fuzzy variable, returned as a `fisvar` object. `varOut` has the same properties as `varIn` except the membership function with the specified name is removed.

See Also

`addMF`

Topics

"Build Fuzzy Systems at the Command Line" on page 2-31

Introduced in R2018b

removeOutput

Remove output variable from fuzzy inference system

Syntax

```
fisOut = removeOutput(fisIn,outputName)
```

Description

`fisOut = removeOutput(fisIn,outputName)` removes the output variable with the name `outputName` from fuzzy inference system `fisIn` and returns the resulting fuzzy system in `fisOut`.

Examples

Remove Output Variable from Fuzzy Inference System

Load fuzzy system.

```
fis = readfis("mam22");
```

View the output variables of `fis`.

```
fis.Outputs
```

```
ans =  
1x2 fisvar array with properties:
```

```
    Name  
    Range  
    MembershipFunctions
```

```
Details:
```

	Name	Range	MembershipFunctions
1	"force"	-5 5	{1x4 fismf}
2	"force2"	-5 5	{1x4 fismf}

View the rules of `fis`.

```
fis.Rules
```

```
ans =  
1x4 fisrule array with properties:
```

```
    Description  
    Antecedent  
    Consequent  
    Weight  
    Connection
```

Details:

Description

```

1 "angle==small & velocity==small => force=negBig, force2=posBig2 (1)"
2 "angle==small & velocity==big => force=negSmall, force2=posSmall2 (1)"
3 "angle==big & velocity==small => force=posSmall, force2=negSmall2 (1)"
4 "angle==big & velocity==big => force=posBig, force2=negBig2 (1)"

```

Remove the forceBig output variable.

```
fis = removeOutput(fis, "force2");
```

View the updated output variables.

fis.Outputs

```
ans =
  fisvar with properties:
      Name: "force"
      Range: [-5 5]
  MembershipFunctions: [1x4 fismf]
```

View the updated rules.

fis.Rules

```
ans =
  1x4 fisrule array with properties:
      Description
      Antecedent
      Consequent
      Weight
      Connection
```

Details:

Description

```

1 "angle==small & velocity==small => force=negBig (1)"
2 "angle==small & velocity==big => force=negSmall (1)"
3 "angle==big & velocity==small => force=posSmall (1)"
4 "angle==big & velocity==big => force=posBig (1)"

```

force2 has been removed from the variables and rules of fis.

Input Arguments

fisIn — Fuzzy inference system

mamfis object | sugfis object | mamfistype2 object | sugfistype2 object

Fuzzy inference system, specified as one of the following objects.

- `mamfis` object — Mamdani fuzzy inference system
- `sugfis` object — Sugeno fuzzy inference system
- `mamfistype2` object — Type-2 Mamdani fuzzy inference system
- `sugfistype2` object — Type-2 Sugeno fuzzy inference system

outputName — Output variable name`string | character vector`

Output variable name, specified as a string or character vector.

Output Arguments

fisOut — Updated fuzzy inference system`mamfis object | sugfis object | mamfistype2 object | sugfistype2 object`

Updated fuzzy inference system, returned as one of the following objects.

- `mamfis` object — Mamdani fuzzy inference system
- `sugfis` object — Sugeno fuzzy inference system
- `mamfistype2` object — Type-2 Mamdani fuzzy inference system
- `sugfistype2` object — Type-2 Sugeno fuzzy inference system

`fisOut` has the same properties as `fisIn` except:

- The input variable with the specified name is removed.
- The specified input variable is removed from any fuzzy rules. If a rule has only the specified input variable in its antecedent, then the entire rule is removed. If a rule has more than one input variable in its antecedent, then the specified input variable is removed from the antecedent.

See Also

`addOutput | fisvar`

Topics

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced in R2018b

rmmf

(To be removed) Remove membership function from fuzzy inference system

Note rmmf will be removed in a future release. Use removeMF instead. For more information, see “Compatibility Considerations”.

Syntax

```
outfis = rmmf(infis,varType,varIndex,'mf',mfIndex)
```

Description

`outfis = rmmf(infis,varType,varIndex,'mf',mfIndex)` Removes the specified membership function from a given input or output variable of the fuzzy system `infis`.

Examples

Remove Membership Function From Variable

Create a fuzzy inference system.

```
fis = newfis('mysys');
```

Add an input variable with a single membership function to the system.

```
fis = addvar(fis,'input','temperature',[0 100]);
fis = addmf(fis,'input',1,'cold','trimf',[0 30 60]);
```

View the variable properties.

```
getfis(fis,'input',1)

ans = struct with fields:
    Name: 'temperature'
    NumMFs: 1
        mf1: 'cold'
        range: [0 100]
```

Remove the membership function. To do so, remove membership function 1 from input 1.

```
fis = rmmf(fis,'input',1,'mf',1);
```

View the variable properties.

```
getfis(fis,'input',1)

ans = struct with fields:
    Name: 'temperature'
    NumMFs: 0
```

```
range: [0 100]
```

The variable now has no membership function.

Input Arguments

inFIS — Fuzzy system

mamfis object | sugfis object

Fuzzy system, specified as a FIS object.

varType — Variable type

'input' | 'output'

Variable type, specified as either 'input' or 'output'.

varIndex — Variable index

positive integer

Variable index, specified as a positive integer.

mfIndex — Membership function index

positive integer

Membership function index, specified as a positive integer.

Output Arguments

outFIS — Updated fuzzy system

mamfis object | sugfis object

Updated fuzzy system, returned as a FIS object.

Compatibility Considerations

rmmf will be removed

Not recommended starting in R2018b

rmmf will be removed in a future release. Use removeMF instead. There are differences between these functions that require updates to your code.

Update Code

The following table shows some typical usages of rmmf and how to update your code to use removeMF instead. Previously, you specified the index of the variable from which you wanted to remove the membership function and the index of the membership function that you wanted to remove. Now, to remove a membership function, specify the variable name and the membership function name.

If your code has this form:	Use this code instead:
<code>fis = rmmf(fis,'input',1,'mf',1)</code>	<code>fis = removeMF(fis,"service","poor")</code>

If your code has this form:	Use this code instead:
<code>fis = rmmf(fis,'output',1,'mf',1)</code>	<code>fis = removeMF(fis,"tip","cheap")</code>

See Also

`removeMF` | `addMF` | `addRule` | `addvar` | `plotmf` | `rmvar`

Topics

“Membership Functions” on page 1-9

“The Membership Function Editor” on page 2-20

Introduced before R2006a

rmvar

(To be removed) Remove variables from fuzzy inference system

Note `rmvar` will be removed in a future release. Use `removeInput` or `removeOutput` instead. For more information, see “Compatibility Considerations”.

Syntax

```
outfis = rmvar(infis,varType,varIndex)
[outfis,errorStr] = rmvar( ___ )
```

Description

`outfis = rmvar(infis,varType,varIndex)` removes the input or output variable with the specified index from the fuzzy system `infis`.

This command automatically alters the rule list to keep its size consistent with the current number of variables. You must delete from the FIS any rule that contains a variable you want to remove before removing it. You cannot remove a fuzzy variable currently in use in the rule list.

`[outfis,errorStr] = rmvar(___)` returns any errors as a character vector.

Examples

Remove Membership Function From Variable

Create a fuzzy inference system.

```
fis = newfis('mysys');
```

Add an input variable with a single membership function to the system.

```
fis = addvar(fis,'input','temperature',[0 100]);
fis = addmf(fis,'input',1,'cold','trimf',[0 30 60]);
```

View the variable properties.

```
getfis(fis,'input',1)
ans = struct with fields:
    Name: 'temperature'
    NumMFs: 1
    mf1: 'cold'
    range: [0 100]
```

Remove the membership function. To do so, remove membership function 1 from input 1.

```
fis = rmmf(fis,'input',1,'mf',1);
```

View the variable properties.

```
getfis(fis,'input',1)
ans = struct with fields:
    Name: 'temperature'
    NumMFs: 0
    range: [0 100]
```

The variable now has no membership function.

Input Arguments

infis — Fuzzy system

mamfis object | sugfis object

Fuzzy system, specified as a FIS object.

varType — Variable type

'input' | 'output'

Variable type, specified as either 'input' or 'output'.

varIndex — Variable index

positive integer

Variable index, specified as a positive integer.

Output Arguments

outfis — Updated fuzzy system

mamfis object | sugfis object

Updated fuzzy system, returned as a FIS object.

errorStr — Error messages

character vector

Error messages, returned as a character vector.

Compatibility Considerations

rmvar will be removed

Not recommended starting in R2018b

rmvar will be removed in a future release. To remove input or output variables from a fuzzy system, use `removeInput` or `removeOutput`, respectively, instead. There are differences between these functions that require updates to your code.

Update Code

This table shows some typical usages of `rmvar` and how to update your code to use `removeInput` or `removeOutput` instead. Previously, you specified the index of the variable that you wanted to remove. Now, to remove a variable, specify the variable name.

If your code has this form:	Use this code instead:
<code>fis = rmvar(fis,'input',1)</code>	<code>fis = removeInput(fis,"service")</code>
<code>fis = rmvar(fis,'output',1)</code>	<code>fis = removeOutput(fis,"tip")</code>

Previously, you had to delete any rules from your fuzzy system that contained the variable you wanted to remove. `removeInput` and `removeOutput` automatically remove these variables from the rule set of your fuzzy system.

See Also

`removeInput` | `removeOutput` | `addMF` | `addRule` | `addvar` | `rmmf`

Introduced before R2006a

ruleedit

Open Rule Editor

Syntax

```
ruleedit(fis)
ruleedit(fileName)
```

Description

Use the Rule Editor to view or modify the rules of your fuzzy system. To define rules, you must specify the input and output variables of your FIS and their corresponding membership functions.

The **Fuzzy Logic Designer** app consists of several interactive interfaces for creating a fuzzy inference system (FIS), including the Rule Editor. For more information on interactively creating fuzzy systems, see “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14.

`ruleedit(fis)` opens the Rule Editor and loads the fuzzy inference system `fis`.

`ruleedit(fileName)` opens the Rule Editor and loads a fuzzy inference system from the file specified by `fileName`.

Examples


Open Rule Editor

Load or create a fuzzy inference system object. For this example, load the fuzzy system from a file.

```
fis = readfis('tipper');
```

Open the Rule Editor for this fuzzy system.

```
ruleedit(fis)
```



Input Arguments

fis – Fuzzy inference system

mamfis object | sugfis object

Fuzzy inference system, specified as either a mamfis or sugfis object in the MATLAB workspace.

fileName – File name

string | character vector

File name specified as a string or character vector with or without the `.fis` extension. This file must be in the current working directory or on the MATLAB path.

Compatibility Considerations

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

See Also

Apps

Fuzzy Logic Designer

Functions

`addRule` | `showrule` | `mfedit` | `ruleview` | `surfview`

Topics

“The Rule Editor” on page 2-25

Introduced before R2006a

ruleview

Open Rule Viewer

Syntax

```
ruleview(fis)
ruleview(fileName)
```

Description

Use the Rule Viewer to view the inference process for your fuzzy system. You can adjust the input values and view the corresponding output of each fuzzy rule, the aggregated output fuzzy set, and the defuzzified output value. To view the inference process, you must specify the input and output variables of your FIS, their corresponding membership functions, and the fuzzy rules for your system.

The **Fuzzy Logic Designer** app consists of several interactive interfaces for creating a fuzzy inference system (FIS), including the Rule Viewer. For more information on interactively creating fuzzy systems, see “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14.

`ruleview(fis)` opens the Rule Viewer and loads the fuzzy inference system `fis`.

`ruleview(fileName)` opens the Rule Viewer and loads a fuzzy inference system from the file specified by `fileName`.

Examples


Open Rule Viewer

Load or create a fuzzy inference system object. For this example, load the fuzzy system from a file.

```
fis = readfis('tipper');
```

Open the Rule Viewer for this fuzzy system.

```
ruleview(fis)
```

Input Arguments

fis – Fuzzy inference system

mamfis object | sugfis object

Fuzzy inference system, specified as either a mamfis or sugfis object in the MATLAB workspace.

fileName – File name

string | character vector

File name specified as a string or character vector with or without the .fis extension. This file must be in the current working directory or on the MATLAB path.

Compatibility Considerations

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

See Also

Apps

Fuzzy Logic Designer

Functions

`ruleedit` | `addRule` | `showrule` | `mfedit` | `surfview`

Topics

“The Rule Viewer” on page 2-27

Introduced before R2006a

setfis

(To be removed) Set fuzzy system properties

Note `setfis` will be removed in a future release. Set fuzzy inference system properties using dot notation instead. For more information, see “Compatibility Considerations”.

Syntax

```
outfis = setfis(infis, fisPropName, fisPropValue)
outfis = setfis(infis, varType, varIndex, varPropName, varPropValue)
outfis = setfis(infis, varType, varIndex, 'mf', mfIndex, mfPropName, mfPropValue)
```

Description

`outfis = setfis(infis, fisPropName, fisPropValue)` sets the specified property of the fuzzy system `infis` to the specified value.

`outfis = setfis(infis, varType, varIndex, varPropName, varPropValue)` sets the specified property of a variable in a fuzzy system.

`outfis = setfis(infis, varType, varIndex, 'mf', mfIndex, mfPropName, mfPropValue)` sets the specified property of a membership function for an input or output variable in a fuzzy system.

Examples

Set Fuzzy Inference System Properties

Load a fuzzy inference system.

```
fis = readfis('tipper');
```

Set the defuzzification method to the bisector method.

```
fis = setfis(fis, 'defuzzmethod', 'bisector');
```

View the defuzzification method of the updated FIS.

```
getfis(fis, 'defuzzmethod')
```

```
ans =
'bisector'
```

Set Variable Properties in FIS

Load a fuzzy inference system.

```
fis = readfis('tipper');
```

Set the name of the first input variable to 'help'.

```
fis = setfis(fis, 'input', 1, 'name', 'help');
```

View the name of the variable in the updated system.

```
getfis(fis, 'input', 1, 'name')
```

```
ans =  
'help'
```

Set Membership Function Properties in FIS

Load a fuzzy inference system.

```
fis = readfis('tipper');
```

Change the type of the second membership function of the first input variable to a triangular membership function.

```
fis = setfis(fis, 'input', 1, 'mf', 2, 'type', 'trimf');
```

When changing the type of a membership function, you must also set the parameters accordingly. To convert the original Gaussian membership function parameters to triangular membership function parameters, use the `mf2mf` command.

```
gaussParams = getfis(fis, 'input', 1, 'mf', 2, 'params');  
triParams = mf2mf(gaussParams, 'gaussmf', 'trimf');
```

Set the membership function parameters to the converted values.

```
fis = setfis(fis, 'input', 1, 'mf', 2, 'params', triParams);
```

View the updated membership function properties.

```
getfis(fis, 'input', 1, 'mf', 2)  
  
ans = struct with fields:  
    Name: 'good'  
    Type: 'trimf'  
    params: [1.4680 5 8.5320]
```

Input Arguments

infis — Fuzzy system

mamfis object | sugfis object

Fuzzy system, specified as a FIS object.

fisPropName — Fuzzy system property name

string | character vector

Fuzzy system, specified as one of the following values.

- 'name'
- 'type'
- 'andmethod'
- 'ormethod'
- 'impmethod'
- 'aggmethod'
- 'defuzzmethod'

fisPropValue — Fuzzy system property value

string | character vector

Fuzzy system property value, specified as a string or character vector.

varType — Variable type

'input' | 'output'

Variable type, specified as either 'input' or 'output'.

varIndex — Variable index

positive integer

Variable index, specified as a positive integer.

varPropName — Variable property name

'name' | 'range'

Variable property name, specified as either 'name' or 'range'.

varPropValue — Variable property value

string | character vector | two-element row vector

Variable property value, specified as a character vector or string (when varPropName is 'name') or a two-element row vector (when varPropName is 'range').

mfIndex — Membership function index

positive integer

Membership function index, specified as a positive integer.

mfPropName — Membership function property name

'name' | 'type' | 'params'

Membership function property name, specified as 'name', 'type', or 'params'.

mfPropValue — Membership function property value

string | character vector | row vector

Membership function property value, specified as a character vector or string (when mfPropName is 'name' or 'type') or a two-element row vector (when mfPropName is 'params').

Output Arguments

outfis — Updated fuzzy system

mamfis object | sugfis object

Updated fuzzy system, returned as a FIS object.

Compatibility Considerations

setfis will be removed

Not recommended starting in R2018b

`setfis` will be removed in a future release. Set fuzzy inference system properties using dot notation instead. There are differences between these approaches that require updates to your code.

Update Code

This table shows some typical usages of `setfis` for setting fuzzy inference system properties and how to update your code to use dot notation instead.

If your code has this form:	Use this code instead:
<code>fis = setfis(fis, 'andmethod', 'prod')</code>	<code>fis.AndMethod = 'prod'</code>
<code>fis = setfis(fis, 'input', 1, ... 'name', 'service')</code>	<code>fis.Inputs(1).Name = "service"</code>
<code>fis = setfis(fis, 'input', 2, ... 'mf', 1, ... params, [5 10 15])</code>	<code>fis.Inputs(2).MembershipFunctions(1).Parameters = ... [5 10 15]</code>

Previously, fuzzy inference systems were represented as structures. Now, fuzzy inference systems are represented as objects. Fuzzy inference system object properties have different names than the corresponding structure fields. For more information on fuzzy inference system objects, see `mamfis` and `sugfis`.

See Also

`getfis`

Introduced before R2006a

setTunable

Package: fuzzy.tuning

Set specified parameter settings as tunable or nontunable

Syntax

```
paramsOut = setTunable(paramsIn,tunableFlag)
```

Description

`paramsOut = setTunable(paramsIn,tunableFlag)` sets the `paramsIn` parameters as tunable or nontunable using `tunableFlag`. The modified tunable parameter settings are returned in `paramsOut`.

Examples

Specify Tunability of Parameter Settings

Create a fuzzy inference system, and define the tunable parameter settings of inputs, outputs, and rules.

Create a FIS, and obtain its tunable settings.

```
fis = mamfis("NumInputs",2,"NumOutputs",2);  
[in,out,rule] = getTunableSettings(fis);
```

You can specify all the input variables, output variables, or rules as tunable or nontunable. For example, set all the output variable settings as nontunable.

```
out = setTunable(out,0);
```

You can set the tunability of individual variables or rules. For example, set the first input variable as nontunable.

```
in(1) = setTunable(in(1),0);
```

You can set individual membership functions as nontunable. For example, set the first membership function of input 2 as nontunable.

```
in(2).MembershipFunctions(1) = setTunable(in(2).MembershipFunctions(1),0);
```

You can also specify the tunability of a subset of variables or rules. For example, set the first two rules as nontunable.

```
rule(1:2) = setTunable(rule(1:2),0);
```

Input Arguments

paramsIn — Tunable parameter settings

array | VariableSettings object | RuleSettings object | MembershipFunctionSettings object | MembershipFunctionSettingsType2 object

Tunable parameter settings, specified as one of the following:

- VariableSettings object or an array of such objects
- RuleSettingsObject object or an array of such objects
- MembershipFunctionSettings object or an array of such objects
- MembershipFunctionSettingsType2 object or an array of such objects

array of input, output, and rule parameter settings of a fuzzy system. To obtain these parameter settings, use `getTunableSettings` with the input FIS. `paramsetIn` can be the input parameter, the output parameter, the rule parameter, or some combination of these parameters as an array. The contents of the array depend on which parameters you would like to set.

tunableFlag — Parameter tunability

true or 1 | false or 0

Parameter tunability for the parameters specified in `paramsIn`, specified as a logical 1 (tunable) or 0 (nontunable).

Output Arguments

paramsOut — Modified tunable parameter settings

VariableSettings object | RuleSettings object | MembershipFunctionSettings object | MembershipFunctionSettingsType2 object | vector

Modified tunable parameter settings, returned as one of the following:

- VariableSettings object or an array of such objects
- RuleSettingsObject object or an array of such objects
- MembershipFunctionSettings object or an array of such objects
- MembershipFunctionSettingsType2 object or an array of such objects

`paramsOut` is the same as `paramsetIn`, except with all tunable parameters set to the value specified in `tunableFlag`.

See Also

`mamfis` | `sugfis` | `getTunableSettings` | `tunefis`

Introduced in R2019a

setTunableValues

Specify tunable parameter values of a fuzzy inference system

Syntax

```
fisOut = setTunableValues(fisIn,paramset,paramvals)
___ = setTunableValues( ___, 'IgnoreInvalidParameters',ignoreInvalid)
```

Description

`fisOut = setTunableValues(fisIn,paramset,paramvals)` sets the tunable parameter values of fuzzy inference system `fisIn` and returns the resulting fuzzy system in `fisOut`. To specify the parameters to set, use `paramset`. Specify the new parameter values using `paramvals`.

`___ = setTunableValues(___, 'IgnoreInvalidParameters',ignoreInvalid)` sets a flag for ignoring invalid parameters values.

Examples

Specify Tunable Parameter Values of a FIS

Create a fuzzy inference system and define the tunable parameter settings of inputs, outputs, and rules.

```
fis = mamfis('Name','fis1','NumInputs',2,'NumOutputs',1);
[in,out,rule] = getTunableSettings(fis);
```

Obtain tunable parameter values of the inputs, outputs, and rules of the fuzzy inference system.

```
paramVals = getTunableValues(fis,[in;out;rule]);
```

Redefine some of the values and update the tunable parameter values of the FIS.

```
paramVals(1:3) = [0 0 1];
fis = setTunableValues(fis,[in;out;rule],paramVals);
```

Input Arguments

fisIn – Fuzzy inference system

`mamfis` object | `sugfis` object | `mamfistype2` object | `sugfistype2` object | `fistree` object

Fuzzy inference system, specified as a `mamfis`, `sugfis`, `mamfistype2`, `sugfistype2`, or `fistree` object.

paramset – Tunable parameter settings

array

Tunable parameter settings, specified as an array of input, output, and rule parameter settings in the input FIS. To obtain these parameter settings, use the `getTunableSettings` function with the input `fis`.

`paramset` can be the input, output, or rule parameter settings, or any combination of these settings.

paramvals — Tunable parameter values

array

Tunable parameter values, specified as an array. The order of the values in `paramvals` matches the order of the parameters in `paramset`. To obtain the array of parameter values for a FIS, use `getTunableValues`.

ignoreInvalid — Flag to ignore invalid parameters

array

Flag to ignore invalid parameters, specified as either `true` or `false`. If `true`, invalid `paramvals` are replaced with the existing parameter values of a fuzzy system.

Output Arguments**fisOut — Modified fuzzy inference system**

`mamfis` object | `sugfis` object | `mamfistype2` object | `sugfistype2` object | `fistree` object

Modified fuzzy inference system, returned as a `mamfis`, `sugfis`, `mamfistype2`, or `sugfistype2`, or `fistree` object.

`fisOut` is the same as `fisIn` except that the parameters specified by `paramset` have the values specified by `paramvals`.

See Also

`mamfis` | `sugfis` | `mamfistype2` | `sugfistype2` | `getTunableSettings` | `getTunableValues` | `tunefis`

Introduced in R2019a

showfis

(To be removed) Display annotated fuzzy inference system

Note showfis will be removed in a future release. View the properties of your FIS directly instead. For more information, see “Compatibility Considerations”.

Syntax

```
showfis(fis)
```

Description

showfis(fis) prints a version of the fuzzy inference system, fis, allowing you to see the properties of the system.

Examples

Display FIS Information

Display information for the 'tipper' fuzzy system.

```
a = readfis('tipper');
showfis(a)
```

```

1. Name           tipper
2. Type           mamdani
3. Inputs/Outputs [2 1]
4. NumInputMFs   [3 2]
5. NumOutputMFs  3
6. NumRules      3
7. AndMethod     min
8. OrMethod      max
9. ImpMethod     min
10. AggMethod    max
11. DefuzzMethod centroid
12. InLabels     service
13.              food
14. OutLabels    tip
15. InRange      [0 10]
16.              [0 10]
17. OutRange     [0 30]
18. InMFLabels  poor
19.              good
20.              excellent
21.              rancid
22.              delicious
23. OutMFLabels cheap
24.              average
25.              generous
26. InMFTypes    gaussmf
```

```
27.          gaussmf
28.          gaussmf
29.          trapmf
30.          trapmf
31. OutMFTypes trimf
32.          trimf
33.          trimf
34. InMFParams [1.5 0 0 0]
35.          [1.5 5 0 0]
36.          [1.5 10 0 0]
37.          [0 0 1 3]
38.          [7 9 10 10]
39. OutMFParams [0 5 10 0]
40.          [10 15 20 0]
41.          [20 25 30 0]
42. Rule Antecedent [1 1]
43.          [2 0]
44.          [3 2]
42. Rule Consequent 1
43.          2
44.          3
42. Rule Weight 1
43.          1
44.          1
42. Rule Connection 2
43.          1
44.          2
```

Input Arguments

fis — Fuzzy system

mamfis object | sugfis object

Fuzzy system, specified as a FIS object.

Compatibility Considerations

showfis will be removed

Not recommended starting in R2018b

`showfis` will be removed in a future release. View the properties of your FIS directly instead.

Previously, you could view the properties of your fuzzy system, `myFIS`, using the `showfis` function.

```
showfis(myFIS)
```

Now, you can view the properties directly instead.

```
myFIS
```

To view additional FIS properties, use dot notation. For example, view information about the membership functions of the first input variable.

```
myFIS.Inputs(1).MembershipFunctions
```

For more information on fuzzy inference systems and their properties, see `mamfis` and `sugfis`.

See Also

getfis

Introduced before R2006a

showrule

Display fuzzy inference system rules

Syntax

```
showrule(fis)
showrule(fis,Name,Value)
```

Description

`showrule(fis)` displays the rules in the fuzzy inference system `fis`.

`showrule(fis,Name,Value)` displays rules using options specified by one or more `Name,Value` arguments.

Examples

Display All Rules for a Fuzzy Inference System

Load fuzzy inference system.

```
fis = readfis('tipper');
```

Display rules using linguistic expressions.

```
showrule(fis)
ans = 3x78 char array
    '1. If (service is poor) or (food is rancid) then (tip is cheap) (1)      '
    '2. If (service is good) then (tip is average) (1)                      '
    '3. If (service is excellent) or (food is delicious) then (tip is generous) (1)'
```

Display rules using symbolic expressions.

```
showrule(fis,'Format','symbolic')
ans = 3x65 char array
    '1. (service==poor) | (food==rancid) => (tip=cheap) (1)                '
    '2. (service==good) => (tip=average) (1)                                '
    '3. (service==excellent) | (food==delicious) => (tip=generous) (1)'
```

Display rules using membership function indices.

```
showrule(fis,'Format','indexed')
ans = 3x15 char array
    '1 1, 1 (1) : 2 '
    '2 0, 2 (1) : 1 '
    '3 2, 3 (1) : 2 '
```

Select Fuzzy Rules to Display

Load fuzzy inference system.

```
fis = readfis('tipper');
```

Display the first and third rules.

```
showrule(fis, 'RuleIndex', [1 3])
```

```
ans = 2x78 char array
    '1. If (service is poor) or (food is rancid) then (tip is cheap) (1)      '
    '3. If (service is excellent) or (food is delicious) then (tip is generous) (1)'
```

Display Fuzzy Rules in German Language

Load fuzzy inference system.

```
fis = readfis('tipper');
```

Display the rules in German using the 'deutsch' language.

```
showrule(fis, 'Language', 'deutsch')
```

```
ans = 3x85 char array
    '1. Wenn (service ist poor) oder (food ist rancid) dann (tip ist cheap) (1)      '
    '2. Wenn (service ist good) dann (tip ist average) (1)                          '
    '3. Wenn (service ist excellent) oder (food ist delicious) dann (tip ist generous) (1)'
```

Input Arguments

fis — Fuzzy inference system

mamfis object | sugfis object | mamfistype2 object | sugfistype2 object

Fuzzy inference system, specified as one of the following:

- mamfis object — Mamdani fuzzy inference system
- sugfis object — Sugeno fuzzy inference system
- mamfistype2 object — Type-2 Mamdani fuzzy inference system
- sugfistype2 object — Type-2 Sugeno fuzzy inference system

Name-Value Pair Arguments

Specify optional pairs of arguments as `Name1=Value1, ..., NameN=ValueN`, where `Name` is the argument name and `Value` is the corresponding value. Name-value arguments must appear after other arguments, but the order of the pairs does not matter.

Before R2021a, use commas to separate each name and value, and enclose Name in quotes.

Example: `showrule(fis,"Format","symbolic")`

Before R2021a, use commas to separate each name and value, and enclose Name in quotes.

Example: `showrule(fis,Format="symbolic")`

RuleIndex — Rules to display

positive integer | vector of positive integers

Rules to display, specified as one of the following values.

- Positive integer — Index of a single rule to display
- Vector of positive integers — Indices of multiple rules to display

The default vector includes the indices for all the rules in `fis`.

Format — Rule format

"verbose" (default) | "symbolic" | "indexed"

Rule format, specified as one of the following values.

- "verbose" — Use linguistic expressions.
'If (service is poor) or (food is rancid) then (tip is cheap) (1)'

The rule weight is displayed in parentheses at the end of the rule.

You can specify the rule language using the `Language` option.

- "symbolic" — Use language-neutral symbolic expressions.
'(service==poor) | (food==rancid) => (tip=cheap) (1)'

The symbolic rules use the following symbols.

Rule Component	Symbol
AND	&
OR	
IS (in antecedent)	==
IS (in consequent)	=
IS NOT	~=
Implication (then)	=>

The rule weight is displayed in parentheses at the end of the rule.

- "indexed" — Use input and output membership function (MF) indices and integer representation of fuzzy operators.

The indexed rules display in the following format:

'<input MFs>, <output MFs>, (<weight>) : <logical operator - 1 (AND), 2 (OR)>'

For example:

'1 1, 1 (1) : 2'

To indicate NOT operations for input and output membership functions, the software uses negative indices. For example, to indicate "not the second membership function," the software uses -2.

To indicate a don't care condition for an input or output membership function, the software uses 0.

Language — Rule language

"english" (default) | "français" | "deutsch"

Rule language for "verbose" format, specified as one of the following values.

- "english" — Display rules in English.

```
'If (service is poor) or (food is rancid) then (tip is cheap) (1)'
```

- "français" — Display rules in French.

```
'Si (service est poor) ou (food est rancid) alors (tip est cheap) (1)'
```

- "deutsch" — Display rules in German.

```
'Wenn (service ist poor) oder (food ist rancid) dann (tip ist cheap) (1)'
```

The software displays the FIS rules using the following keywords.

Rule Component	English	French	German
Start of antecedent	if	si	wenn
AND	and	et	und
OR	or	ou	oder
Start of consequent (implication)	then	alors	dann
IS	is	est	ist
IS NOT	is not	n'est_pas	ist nicht

Compatibility Considerations

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

See Also

addRule | ruleedit

Introduced before R2006a

sigmf

Sigmoidal membership function

Syntax

```
y = sigmf(x,params)
```

Description

This function computes fuzzy membership values using a sigmoidal membership function. You can also compute this membership function using a `fismf` object. For more information, see “`fismf` Object” on page 8-241.

This membership function is related to the `dsigmf` and `psigmf` membership functions.

`y = sigmf(x,params)` returns fuzzy membership values computed using the sigmoidal membership function given by:

$$f(x; a_k, c_k) = \frac{1}{1 + e^{-a_k(x - c_k)}}$$

To define the membership function parameters, specify `params` as the vector `[a c]`.

Membership values are computed for each input value in `x`.

Examples

Sigmoidal Membership Function

Specify input values across the universe of discourse.


```
x = 0:0.1:10;
```

Evaluate membership function for the input values.

```
y = sigmf(x,[2 4]);
```

Plot the membership function.

```
plot(x,y)
title('sigmf, P = [2 4]')
xlabel('x')
ylabel('Degree of Membership')
ylim([-0.05 1.05])
```



Input Arguments

x — Input values

scalar | vector

Input values for which to compute membership values, specified as a scalar or vector.

params — Membership function parameters

vector of length four

Membership function parameters, specified as the vector $[a \ c]$. To open the membership function to the left or right, specify a negative or positive value for a , respectively. The magnitude of a controls the width of the transition area, and c defines the center of the transition area.

Output Arguments

y — Membership value

scalar | vector

Membership value returned as a scalar or a vector. The dimensions of y match the dimensions of x . Each element of y is the membership value computed for the corresponding element of x .

Alternative Functionality

fismf Object

You can create and evaluate a `fismf` object that implements the `sigmf` membership function.

```
mf = fismf("sigmf",P);  
Y = evalmf(mf,X);
```

Here, `X`, `P`, and `Y` correspond to the `x`, `params`, and `y` arguments of `sigmf`, respectively.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using MATLAB® Coder™.

See Also

`fismf` | `fismftype2` | `psigmf` | `gaussmf` | `gauss2mf` | `gbellmf` | `trimf` | `trapmf` | `linsmf` | `linzmf` | `pimf` | `smf` | `zmf` | `dsigmf`

Topics

“Membership Functions” on page 1-9

Introduced before R2006a

smf

S-shaped membership function

Syntax

```
y = smf(x,params)
```

Description

This function computes fuzzy membership values using a spline-based S-shaped membership function. You can also compute this membership function using a `fismf` object. For more information, see “`fismf` Object” on page 8-244.

This membership function is related to the `zmf` and `pimf` membership functions.

`y = smf(x,params)` returns fuzzy membership values computed using the spline-based S-shaped membership function given by:

$$f(x; a, b) = \begin{cases} 0, & x \leq a \\ 2\left(\frac{x-a}{b-a}\right)^2, & a \leq x \leq \frac{a+b}{2} \\ 1-2\left(\frac{x-b}{b-a}\right)^2, & \frac{a+b}{2} \leq x \leq b \\ 1, & x \geq b \end{cases}$$

To define the membership function parameters, specify `params` as the vector `[a b]`.

Membership values are computed for each input value in `x`.

Examples

S-Shaped Membership Function

Specify input values across the universe of discourse.


```
x = 0:0.1:10;
```

Evaluate membership function for the input values.

```
y = smf(x,[1 8]);
```

Plot the membership function.

```
plot(x,y)
title('smf, P = [1 8]')
xlabel('x')
ylabel('Degree of Membership')
ylim([-0.05 1.05])
```



Input Arguments

x — Input values

scalar | vector

Input values for which to compute membership values, specified as a scalar or vector.

params — Membership function parameters

vector of length two

Membership function parameters, specified as the vector $[a \ b]$. Parameter a defines the *foot* of the membership function, and b defines its *shoulder*.

Output Arguments

y — Membership value

scalar | vector

Membership value returned as a scalar or a vector. The dimensions of y match the dimensions of x . Each element of y is the membership value computed for the corresponding element of x .

Alternative Functionality

fismf Object

You can create and evaluate a `fismf` object that implements the `smf` membership function.

```
mf = fismf("smf",P);  
Y = evalmf(mf,X);
```

Here, `X`, `P`, and `Y` correspond to the `x`, `params`, and `y` arguments of `smf`, respectively.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using MATLAB® Coder™.

See Also

`fismf` | `fismftype2` | `psigmf` | `sigmf` | `gaussmf` | `gauss2mf` | `gbellmf` | `trimf` | `trapmf` | `linsmf` | `linzmf` | `pimf` | `zmf` | `dsigmf`

Topics

“Membership Functions” on page 1-9

Introduced before R2006a

subclust

Find cluster centers using subtractive clustering

Syntax

```
centers = subclust(data,clusterInfluenceRange)
centers = subclust(data,clusterInfluenceRange,Name,Value)
[centers,sigma] = subclust( ___ )
```

Description

`centers = subclust(data,clusterInfluenceRange)` clusters input data using subtractive clustering with the specified cluster influence range, and returns the computed cluster centers. The subtractive clustering algorithm on page 8-249 estimates the number of clusters in the input data.

`centers = subclust(data,clusterInfluenceRange,Name,Value)` clusters data using algorithm options specified by one or more `Name,Value` arguments.

`[centers,sigma] = subclust(___)` returns the sigma values specifying the range of influence of a cluster center in each of the data dimensions.

Examples

Find Cluster Centers Using Subtractive Clustering

Load data set.

```
load clusterDemo.dat
```

Find cluster centers using the same range of influence for all dimensions.

```
C = subclust(clusterDemo,0.6);
```

Each row of `C` contains one cluster center.

`C`

```
C = 3×3
```

```
    0.5779    0.2355    0.5133
    0.7797    0.8191    0.1801
    0.1959    0.6228    0.8363
```

Specify Bounds for Subtractive Clustering

Load data set.

```
load clusterDemo.dat
```

Define minimum and maximum normalization bounds for each data dimension. Use the same bounds for each dimension.

```
dataScale = [-0.2 -0.2 -0.2;
             1.2  1.2  1.2];
```

Find cluster centers.

```
C = subclust(clusterDemo,0.5,'DataScale',dataScale);
```

Specify Options for Subtractive Clustering

Load data set.

```
load clusterDemo.dat
```

Specify the following clustering options:

- Squash factor of 2.0 - Only find clusters that are far from each other.
- Accept ratio 0.8 - Only accept data points with a strong potential for being cluster centers.
- Reject ratio of 0.7 - Reject data points if they do not have a strong potential for being cluster centers.
- Verbosity flag of 0 - Do not print progress information to the command window.

```
options = [2.0 0.8 0.7 0];
```

Find cluster centers, using a different range of influence for each dimension and the specified options.

```
C = subclust(clusterDemo,[0.5 0.25 0.3],'Options',options);
```

Obtain Cluster Influence Range for Each Data Dimension

Load data set.

```
load clusterDemo.dat
```

Cluster data, returning cluster sigma values, S.

```
[C,S] = subclust(clusterDemo,0.5);
```

Cluster sigma values indicate the range of influence of the computed cluster centers in each data dimension.

Input Arguments

data — Data set to be clustered

M-by-*N* array

Data to be clustered, specified as an M -by- N array, where M is the number of data points and N is the number of data dimensions.

clusterInfluenceRange — Range of influence of the cluster center

scalar value in the range [0, 1] | vector

Range of influence of the cluster center for each input and output assuming the data falls within a unit hyperbox, specified as the comma-separated pair consisting of 'ClusterInfluenceRange' one of the following:

- Scalar value in the range [0 1] — Use the same influence range for all inputs and outputs.
- Vector — Use different influence ranges for each input and output.

Specifying a smaller range of influence usually creates more and smaller data clusters, producing more fuzzy rules.

Name-Value Pair Arguments

Specify optional pairs of arguments as `Name1=Value1, ..., NameN=ValueN`, where `Name` is the argument name and `Value` is the corresponding value. Name-value arguments must appear after other arguments, but the order of the pairs does not matter.

Before R2021a, use commas to separate each name and value, and enclose Name in quotes.

Example: `centers = subclust(data,0.5,DataScale=10)`

Before R2021a, use commas to separate each name and value, and enclose Name in quotes.

Example: `centers = subclust(data,0.5,"DataScale",10)`

DataScale — Data scale factors

'auto' (default) | 2-by- N array

Data scale factors for normalizing input and output data into a unit hyperbox, specified as a 2-by- N array, where N is the total number of inputs and outputs. Each column of `DataScale` specifies the minimum value in the first row and the maximum value in the second row for the corresponding input or output data set.

When `DataScale` is 'auto', the `genfis` command uses the actual minimum and maximum values in the data to be clustered.

Options — Clustering options

vector

Clustering options, specified as a vector with the following elements.

Options(1) — Squash factor

1.25 (default) | positive scalar

Squash factor for scaling the range of influence of cluster centers, specified as a positive scalar. A smaller squash factor reduces the potential for outlying points to be considered as part of a cluster, which usually creates more and smaller data clusters.

Options(2) — Acceptance ratio

0.5 (default) | scalar value in the range [0, 1]

Acceptance ratio, defined as a fraction of the potential of the first cluster center, above which another data point is accepted as a cluster center, specified as a scalar value in the range [0, 1]. The acceptance ratio must be greater than the rejection ratio.

Options(3) — Rejection ratio

0.15 (default) | scalar value in the range [0, 1]

Rejection ratio, defined as a fraction of the potential of the first cluster center, below which another data point is rejected as a cluster center, specified as a scalar value in the range [0, 1]. The rejection ratio must be less than acceptance ratio.

Options(4) — Information display flag

false (default) | true

Information display flag indicating whether to display progress information during clustering, specified as one of the following:

- `false` — Do not display progress information.
- `true` — Display progress information.

Output Arguments

centers — Cluster centers

J-by-*N* array

Cluster centers, returned as a *J*-by-*N* array, where *J* is the number of clusters and *N* is the number of data dimensions.

sigma — Range of influence of cluster centers

N-element row vector

Range of influence of cluster centers for each data dimension, returned as an *N*-element row vector. All cluster centers have the same set of `sigma` values.

Tips

- To generate a fuzzy inference system using subtractive clustering, use the `genfis` command. For example, suppose you cluster your data using the following syntax:

```
C = subclust(data,clusterInfluenceRange,'DataScale',dataScale,'Options',options);
```

where the first *M* columns of `data` correspond to input variables, and the remaining columns correspond to output variables.

You can generate a fuzzy system using the same training data and subtractive clustering configuration. To do so:

- 1 Configure clustering options.

```
opt = genfisOptions('SubtractiveClustering');
opt.ClusterInfluenceRange = clusterInfluenceRange;
opt.DataScale = dataScale;
opt.SquashFactor = options(1);
opt.AcceptRatio = options(2);
```

```

    opt.RejectRatio = options(3);
    opt.Verbose = options(4);
2  Extract input and output variable data.

    inputData = data(:,1:M);
    outputData = data(:,M+1:end);
3  Generate FIS structure.

    fis = genfis(inputData,outputData,opt);

```

The fuzzy system, `fis`, contains one fuzzy rule for each cluster, and each input and output variable has one membership function per cluster. You can generate only Sugeno fuzzy systems using subtractive clustering. For more information, see `genfis` and `genfisOptions`.

Algorithms

Subtractive clustering assumes that each data point is a potential cluster center. The algorithm does the following:

- 1 Calculate the likelihood that each data point would define a cluster center, based on the density of surrounding data points.
- 2 Choose the data point with the highest potential to be the first cluster center.
- 3 Remove all data points near the first cluster center. The vicinity is determined using `clusterInfluenceRange`.
- 4 Choose the remaining point with the highest potential as the next cluster center.
- 5 Repeat steps 3 and 4 until all the data is within the influence range of a cluster center.

The subtractive clustering method is an extension of the mountain clustering method proposed in [2].

References

- [1] Chiu, S., "Fuzzy Model Identification Based on Cluster Estimation," *Journal of Intelligent & Fuzzy Systems*, Vol. 2, No. 3, Sept. 1994.
- [2] Yager, R. and D. Filev, "Generation of Fuzzy Rules by Mountain Clustering," *Journal of Intelligent & Fuzzy Systems*, Vol. 2, No. 3, pp. 209-219, 1994.

See Also

`genfis`

Topics

"Fuzzy Clustering" on page 4-2

"Model Suburban Commuting Using Subtractive Clustering and ANFIS" on page 4-17

Introduced before R2006a

surfview

Open Surface Viewer

Syntax

```
surfview(fis)  
surfview(fileName)
```

Description

Use the Surface Viewer to view the output surface for your fuzzy system. To view the output surface, you must specify the input and output variables of your FIS, their corresponding membership functions, and the fuzzy rules for your system.

The **Fuzzy Logic Designer** app consists of several interactive interfaces for creating a fuzzy inference system (FIS), including the Surface Viewer. For more information on interactively creating fuzzy systems, see “Build Fuzzy Systems Using Fuzzy Logic Designer” on page 2-14.

`surfview(fis)` opens the Surface Viewer and loads the fuzzy inference system `fis`.

`surfview(fileName)` opens the Surface Viewer and loads a fuzzy inference system from the file specified by `fileName`.

Examples


Open Surface Viewer

Load or create a fuzzy inference system object. For this example, load the fuzzy system from a file.

```
fis = readfis('tipper');
```

Open the Surface Viewer for this fuzzy system.

```
surfview(fis)
```



Input Arguments

fis – Fuzzy inference system

mamfis object | sugfis object | mamfistype2 object | sugfistype2 object

Fuzzy inference system, specified as one of the following:

- mamfis object — Mamdani fuzzy inference system
- sugfis object — Sugeno fuzzy inference system
- mamfistype2 object — Type-2 Mamdani fuzzy inference system
- sugfistype2 object — Type-2 Sugeno fuzzy inference system

Note The Surface Viewer is the only interface of the **Fuzzy Logic Designer** app that supports type-2 fuzzy inference systems.

fileName – File name

string | character vector

File name specified as a string or character vector with or without the `.fis` extension. This file must be in the current working directory or on the MATLAB path.

Tips

- For systems with more than two input variables, you can view the output surface for any combination of two inputs. You must specify constant reference values for any other input signals using the **Ref. Input** value.
- By default, the surface plot updates automatically when you change the input or output variable selections or the number of grid points. To disable automatic plot updates, in the **Options** menu, clear the **Always evaluate** option. When this option is disabled, to update the plot, click **Evaluate**.
- To create a smoother plot, increase the **Plot points** value.
- To view the surface from different angles, click and drag on the plot area.

Compatibility Considerations

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

See Also

Apps

Fuzzy Logic Designer

Functions

`gensurf` | `ruleedit` | `ruleview` | `mfedit`

Topics

“The Surface Viewer” on page 2-29

Introduced before R2006a

trapmf

Trapezoidal membership function

Syntax

```
y = trapmf(x,params)
```

Description

This function computes fuzzy membership values using a trapezoidal membership function. You can also compute this membership function using a `fismf` object. For more information, see “`fismf` Object” on page 8-255.

This membership function is related to the `trimf`, `linsmf`, and `linzmf` membership functions.

`y = trapmf(x,params)` returns fuzzy membership values computed using the following trapezoidal membership function:

$$f(x; a, b, c, d) = \max\left(\min\left(\frac{x-a}{b-a}, 1, \frac{d-x}{d-c}\right), 0\right)$$

To define the membership function parameters, specify `params` as the vector `[a b c d]`.

Membership values are computed for each input value in `x`.

Examples

Trapezoid-Shaped Membership Function

Specify input values across the universe of discourse.


```
x = 0:0.1:10;
```

Evaluate membership function for the input values.

```
y = trapmf(x,[1 5 7 8]);
```

Plot the membership function.

```
plot(x,y)
title('trapmf, P = [1 5 7 8]')
xlabel('x')
ylabel('Degree of Membership')
ylim([-0.05 1.05])
```



Input Arguments

x — Input values

scalar | vector

Input values for which to compute membership values, specified as a scalar or vector.

params — Membership function parameters

vector of length two

Membership function parameters, specified as the vector $[a \ b \ c \ d]$. Parameters b and c define the *shoulders* of the membership function, and a and d define its *feet*.

The shape of the membership function depends on the relative values of b and c .

- When c is greater than b , the resulting membership function is trapezoidal.
- When b is equal to c , the resulting membership function is equivalent to a triangular membership function with parameters $[a \ b \ d]$.
- When c is less than b , the resulting membership function is triangular with a maximum value less than 1.

Output Arguments

y — Membership value

scalar | vector

Membership value returned as a scalar or a vector. The dimensions of **y** match the dimensions of **x**. Each element of **y** is the membership value computed for the corresponding element of **x**.

Alternative Functionality

fismf Object

You can create and evaluate a **fismf** object that implements the **trapmf** membership function.

```
mf = fismf("trapmf",P);  
Y = evalmf(mf,X);
```

Here, **X**, **P**, and **Y** correspond to the **x**, **params**, and **y** arguments of **trapmf**, respectively.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using MATLAB® Coder™.

See Also

[fismf](#) | [fismftype2](#) | [psigmf](#) | [sigmf](#) | [gaussmf](#) | [gauss2mf](#) | [gbellmf](#) | [trimf](#) | [linsmf](#) | [linzmf](#) | [pimf](#) | [smf](#) | [zmf](#) | [dsigmf](#)

Topics

“Membership Functions” on page 1-9

Introduced before R2006a

trimf

Triangular membership function

Syntax

```
y = trimf(x,params)
```

Description

This function computes fuzzy membership values using a triangular membership function. You can also compute this membership function using a `fismf` object. For more information, see “`fismf` Object” on page 8-258.

This membership function is related to the `trapmf`, `linsmf`, and `linzmf` membership functions.

`y = trimf(x,params)` returns fuzzy membership values computed using the following triangular membership function:

$$f(x; a, b, c) = \begin{cases} 0, & x \leq a \\ \frac{x-a}{b-a}, & a \leq x \leq b \\ \frac{c-x}{c-b}, & b \leq x \leq c \\ 0, & c \leq x \end{cases}$$

or, more compactly:

$$f(x; a, b, c) = \max\left(\min\left(\frac{x-a}{b-a}, \frac{c-x}{c-b}\right), 0\right)$$

To define the membership function parameters, specify `params` as the vector `[a b c]`.

Membership values are computed for each input value in `x`.

Examples

Triangle-Shaped Membership Function

Specify input values across the universe of discourse.

```
x = 0:0.1:10;
```


Evaluate membership function for the input values.

```
y = trimf(x,[3 6 8]);
```

Plot the membership function.

```
plot(x,y)
title('trimf, P = [3 6 8]')
```

```
xlabel('x')
ylabel('Degree of Membership')
ylim([-0.05 1.05])
```



Input Arguments

x – Input values

scalar | vector

Input values for which to compute membership values, specified as a scalar or vector.

params – Membership function parameters

vector of length three

Membership function parameters, specified as the vector $[a \ b \ c]$. Parameters a and c define the *feet* of the membership function, and b defines its *peak*.

Output Arguments

y – Membership value

scalar | vector

Membership value returned as a scalar or a vector. The dimensions of y match the dimensions of x . Each element of y is the membership value computed for the corresponding element of x .

Alternative Functionality

fismf Object

You can create and evaluate a `fismf` object that implements the `trimf` membership function.

```
mf = fismf("trimf",P);  
Y = evalmf(mf,X);
```

Here, `X`, `P`, and `Y` correspond to the `x`, `params`, and `y` arguments of `trimf`, respectively.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using MATLAB® Coder™.

See Also

`fismf` | `fismftype2` | `psigmf` | `sigmf` | `gaussmf` | `gauss2mf` | `gbellmf` | `trapmf` | `linsmf` | `linzmf` | `pimf` | `smf` | `zmf` | `dsigmf`

Topics

“Membership Functions” on page 1-9

Introduced before R2006a

tunefis

Tune fuzzy inference system or tree of fuzzy inference systems

Syntax

```
fisout = tunefis(fisin,paramset,in,out)
fisout = tunefis(fisin,paramset,custcostfcn)
fisout = tunefis(___,options)
[fisout,summary] = tunefis(___)
```

Description

`fisout = tunefis(fisin,paramset,in,out)` tunes the fuzzy inference system `fisin` using the tunable parameter settings specified in `paramset` and the training data specified by `in` and `out`.

`fisout = tunefis(fisin,paramset,custcostfcn)` tunes the fuzzy inference system using a function handle to a custom cost function, `custcostfcn`.

`fisout = tunefis(___,options)` tunes the fuzzy inference system with additional options from the object `options` created using `tunefisOptions`.

`[fisout,summary] = tunefis(___)` tunes the fuzzy inference system and returns additional information about the tuning algorithm in `summary`.

Examples

Tune a Fuzzy Inference System

Create the initial fuzzy inference system using `genfis`.

```
x = (0:0.1:10)';
y = sin(2*x)./exp(x/5);
options = genfisOptions('GridPartition');
options.NumMembershipFunctions = 5;
fisin = genfis(x,y,options);
```

Obtain the tunable settings of inputs, outputs, and rules of the fuzzy inference system.

```
[in,out,rule] = getTunableSettings(fisin);
```

Tune the membership function parameters with "anfis".

```
fisout = tunefis(fisin,[in;out],x,y,tunefisOptions("Method","anfis"));
```

ANFIS info:

```
Number of nodes: 24
Number of linear parameters: 10
Number of nonlinear parameters: 15
Total number of parameters: 25
Number of training data pairs: 101
Number of checking data pairs: 0
```

Number of fuzzy rules: 5

Start training ANFIS ...

```

1      0.0694086
2      0.0680259
3      0.0666663
4      0.0653198
Step size increases to 0.011000 after epoch 5.
5      0.0639961
6      0.0626917
7      0.0612787
8      0.0598881
Step size increases to 0.012100 after epoch 9.
9      0.0585193
10     0.0571712

```

Designated epoch number reached. ANFIS training completed at epoch 10.

Minimal training RMSE = 0.0571712

Tune Specific Parameter Setting of Fuzzy Inference System

Create the initial fuzzy inference system using `genfis`.

```

x = (0:0.1:10)';
y = sin(2*x)./exp(x/5);
options = genfisOptions('GridPartition');
options.NumMembershipFunctions = 5;
fisin = genfis(x,y,options);

```

Obtain the tunable settings of inputs, outputs, and rules of the fuzzy inference system.

```
[in,out,rule] = getTunableSettings(fisin);
```

Tune the rule parameter only. In this example, the pattern search method is used.

```
fisout = tunefis(fisin,rule,x,y,tunefisOptions("Method","patternsearch"));
```

Iter	Func-count	f(x)	MeshSize	Method
0	1	0.346649	1	
1	19	0.346649	0.5	Refine Mesh
2	37	0.346649	0.25	Refine Mesh
3	55	0.346649	0.125	Refine Mesh
4	73	0.346649	0.0625	Refine Mesh
5	91	0.346649	0.03125	Refine Mesh
6	109	0.346649	0.01562	Refine Mesh
7	127	0.346649	0.007812	Refine Mesh
8	145	0.346649	0.003906	Refine Mesh
9	163	0.346649	0.001953	Refine Mesh
10	181	0.346649	0.0009766	Refine Mesh
11	199	0.346649	0.0004883	Refine Mesh
12	217	0.346649	0.0002441	Refine Mesh
13	235	0.346649	0.0001221	Refine Mesh
14	253	0.346649	6.104e-05	Refine Mesh


```

15      271      0.346649      3.052e-05      Refine Mesh
16      289      0.346649      1.526e-05      Refine Mesh
17      307      0.346649      7.629e-06      Refine Mesh
18      325      0.346649      3.815e-06      Refine Mesh
19      343      0.346649      1.907e-06      Refine Mesh
20      361      0.346649      9.537e-07      Refine Mesh
Optimization terminated: mesh size less than options.MeshTolerance.

```

Tune a Fuzzy Inference System with Custom Parameter Settings

Create the initial fuzzy inference system using `genfis`.

```

x = (0:0.1:10)';
y = sin(2*x)./exp(x/5);
options = genfisOptions('GridPartition');
options.NumMembershipFunctions = 5;
fisin = genfis(x,y,options);

```

Obtain the tunable settings of inputs, outputs, and rules of the fuzzy inference system.

```
[in,out,rule] = getTunableSettings(fisin);
```

You can tune with custom parameter settings using `setTunable` or dot notation.

Do not tune input 1.

```
in(1) = setTunable(in(1),false);
```

For output 1:

- do not tune membership functions 1 and 2,
- do not tune membership function 3,
- set the minimum parameter range of membership function 4 to -2,
- and set the maximum parameter range of membership function 5 to 2.

```

out(1).MembershipFunctions(1:2) = setTunable(out(1).MembershipFunctions(1:2),false);
out(1).MembershipFunctions(3).Parameters.Free = false;
out(1).MembershipFunctions(4).Parameters.Minimum = -2;
out(1).MembershipFunctions(5).Parameters.Maximum = 2;

```

For the rule settings,

- do not tune rules 1 and 2,
- set the antecedent of rule 3 to non-tunable,
- allow NOT logic in the antecedent of rule 4,
- and do not ignore any outputs in rule 3.

```

rule(1:2) = setTunable(rule(1:2),false);
rule(3).Antecedent.Free = false;
rule(4).Antecedent.AllowNot = true;
rule(3).Consequent.AllowEmpty = false;

```

Set the maximum number of iterations to 20 and tune the fuzzy inference system.

```
opt = tunefisOptions("Method","particleswarm");
opt.MethodOptions.MaxIterations = 20;
fisout = tunefis(fisin,[in;out;rule],x,y,opt);
```

Iteration	f-count	Best f(x)	Mean f(x)	Stall Iterations
0	90	0.3265	1.857	0
1	180	0.3265	4.172	0
2	270	0.3265	3.065	1
3	360	0.3265	3.839	2
4	450	0.3265	3.386	3
5	540	0.3265	3.249	4
6	630	0.3265	3.311	5
7	720	0.3265	2.901	6
8	810	0.3265	2.868	7
9	900	0.3181	2.71	0
10	990	0.3181	2.068	1
11	1080	0.3181	2.692	2
12	1170	0.3165	2.146	0
13	1260	0.3165	1.869	1
14	1350	0.3165	2.364	2
15	1440	0.3165	2.07	0
16	1530	0.3164	1.678	0
17	1620	0.2978	1.592	0
18	1710	0.2977	1.847	0
19	1800	0.2954	1.666	0
20	1890	0.2947	1.608	0

Optimization ended: number of iterations exceeded OPTIONS.MaxIterations.

Prevent Overfitting Using K-Fold Cross-Validation

To prevent the overfitting of your tuned FIS to your training data using k-fold cross validation.

Load training data. This training data set has one input and one output.

```
load fuzex1trnData.dat
```

Create a fuzzy inference system for the training data.

```
opt = genfisOptions('GridPartition');
opt.NumMembershipFunctions = 4;
opt.InputMembershipFunctionType = "gaussmf";
inputData = fuzex1trnData(:,1);
outputData = fuzex1trnData(:,2);
fis = genfis(inputData,outputData,opt);
```

For reproducibility, set the random number generator seed.

```
rng('default')
```

Configure the options for tuning the FIS. Use the default tuning method with a maximum of 30 iterations.

```
tuningOpt = tunefisOptions;
tuningOpt.MethodOptions.MaxGenerations = 30;
```

Configure the following options for using k-fold cross validation.

- Use a k-fold value of 3.
- Compute the moving average of the validation cost using a window of length 2.
- Stop each training-validation iteration when the average cost is 5% greater than the current minimum cost.

```
tuningOpt.KFoldValue = 3;
tuningOpt.ValidationWindowSize = 2;
tuningOpt.ValidationTolerance = 0.05;
```

Obtain the settings for tuning the membership function parameters of the FIS.

```
[in,out] = getTunableSettings(fis);
```

Tune the FIS.

```
[outputFIS,info] = tunefis(fis,[in;out],inputData,outputData,tuningOpt);
```

Single objective optimization:
16 Variable(s)

```
Options:
CreationFcn: @gacreationuniform
CrossoverFcn: @crossoverscattered
SelectionFcn: @selectionstochunif
MutationFcn: @mutationadaptfeasible
```

Generation	Func-count	Best f(x)	Mean f(x)	Stall Generations
1	400	0.2421	0.5109	0
2	590	0.2292	0.4688	0
3	780	0.2292	0.4443	1
4	970	0.2256	0.4145	0
5	1160	0.2165	0.3957	0
6	1350	0.2165	0.3835	1
7	1540	0.2077	0.3548	0
8	1730	0.2077	0.3435	1
9	1920	0.2012	0.3414	0
10	2110	0.1857	0.316	0

Optimization terminated: validation tolerance exceeded.

Cross validation iteration 1: Minimum validation cost 0.294718 found at training cost 0.207704

Single objective optimization:
16 Variable(s)

```
Options:
CreationFcn: @gacreationuniform
CrossoverFcn: @crossoverscattered
SelectionFcn: @selectionstochunif
MutationFcn: @mutationadaptfeasible
```

Generation	Func-count	Best f(x)	Mean f(x)	Stall Generations
1	400	0.2089	0.3924	0
2	590	0.2059	0.3655	0

Optimization terminated: validation tolerance exceeded.

Cross validation iteration 2: Minimum validation cost 0.306682 found at training cost 0.220498

Single objective optimization:

16 Variable(s)

Options:

CreationFcn: @gacreationuniform
CrossoverFcn: @crossoverscattered
SelectionFcn: @selectionstochunif
MutationFcn: @mutationadaptfeasible

Generation	Func-count	Best f(x)	Mean f(x)	Stall Generations
1	400	0.2489	0.3936	0
2	590	0.2438	0.3837	0
3	780	0.2438	0.3779	1
4	970	0.2067	0.3476	0

Optimization terminated: validation tolerance exceeded.


Cross validation iteration 3: Minimum validation cost 0.220104 found at training cost 0.255407

Evaluate the FIS for each of the training input values.

```
outputTuned = evalfis(outputFIS,inputData);
```

Plot the output of the tuned FIS along with the expected training output.

```
plot([outputData,outputTuned])  
legend("Expected Output","Tuned Output","Location","southeast")  
xlabel("Data Index")  
ylabel("Output value")
```



Input Arguments

fisin — Fuzzy inference system

mamfis object | sugfis object | mamfistype2 object | sugfistype2 object | fistree object

Fuzzy inference system, specified as one of the following objects.

- mamfis object — Mamdani fuzzy inference system
- sugfis object — Sugeno fuzzy inference system
- mamfistype2 object — Type-2 Mamdani fuzzy inference system
- sugfistype2 object — Type-2 Sugeno fuzzy inference system
- fistree object — Tree of interconnected fuzzy inference systems

paramset — Tunable parameter settings

array

Tunable parameter settings, specified as an array of input, output, and rule parameter settings in the input FIS. To obtain these parameter settings, use the `getTunableSettings` function with the input `fisin`.

`paramset` can be the input, output, or rule parameter settings, or any combination of these settings.

in — Input training data

matrix

Input training data, specified as an m -by- n matrix, where m is the total number of input datasets and n is the number of inputs. The number of input and output datasets must be the same.

out — Output training data

matrix

Output training data, specified as an m -by- q matrix, where m is the total number of output datasets and q is the number of outputs. The number of input and output datasets must be the same.

options — FIS tuning options

tunefisOptions option set

FIS tuning options, specified as a tunefisOptions object. You can specify the tuning algorithm method and other options for the tuning process.

custcostfcn — custom cost functions

function handle

Custom cost function, specified as a function handle. The custom cost function evaluates `fisout` to calculate its cost with respect to an evaluation criterion, such as input/output data. `custcostfcn` must accept at least one input argument for `fisout` and returns a cost value. You can provide an anonymous function handle to attach additional data for cost calculation, as described in this example:

```
function fitness = custcost(cost,trainingData)
    ...
end
custcostfcn = @(fis)custcost(fis,trainingData);
```

Output Arguments

fisout — Tuned fuzzy inference system

mamfis object | sugfis object | mamfistype2 object | sugfistype2 object | fistree object

Tuned fuzzy inference system, returned as one of the following objects.

- `mamfis` object — Mamdani fuzzy inference system
- `sugfis` object — Sugeno fuzzy inference system
- `mamfistype2` object — Type-2 Mamdani fuzzy inference system
- `sugfistype2` object — Type-2 Sugeno fuzzy inference system
- `fistree` object — Tree of interconnected fuzzy inference systems

`fisout` is the same type of FIS as `fisin`.

summary — Tuning algorithm summary

structure

Tuning algorithm summary, specified as a structure containing the following fields:

- `tuningOutputs` — Algorithm-specific tuning information
- `totalFunctionCount` — Total number of evaluations of the optimization cost function
- `totalRuntime` — Total execution time of the tuning process in seconds

- `errorMessage` — Any error message generated when updating `fisin` with new parameter values

`tuningOutputs` is a structure that contains tuning information for the algorithm specified in `options`. The fields in `tuningOutputs` depend on the specified tuning algorithm. When using k -fold cross validation, `tuningOutputs` is an array of k structures, each containing the tuning information for one training-validation iteration.

When using k -fold validation, `totalFunctionCount` and `totalRuntime` the total function cost function evaluations and total run time across all k training-validation iterations.

See Also

`getTunableSettings` | `tunefisOptions`

Introduced in R2019a

update

Update fuzzy rule using fuzzy inference system

Syntax

```
ruleOut = update(ruleIn, fis)
```

Description

`ruleOut = update(ruleIn, fis)` updates the fuzzy rule `ruleIn` using the information in fuzzy inference system `fis` and returns the resulting fuzzy rule in `ruleOut`.

Examples

Create Fuzzy Rule Using Text Description

Create a fuzzy rule using a verbose text description.

```
rule = fisrule("if service is poor and food is delicious then tip is average (1)");
```

Alternatively, you can specify the same rule using a symbolic text description.

```
rule = fisrule("service==poor & food==delicious => tip=average")
```

```
rule =  
  fisrule with properties:  
  
  Description: "service==poor & food==delicious => tip=average (1)"  
  Antecedent: []  
  Consequent: []  
  Weight: 1  
  Connection: 1
```

Before using `rule` with a fuzzy system, update the rule `Antecedent` and `Consequent` properties using the `update` function.

```
fis = readfis("tipper");  
rule = update(rule, fis)
```

```
rule =  
  fisrule with properties:  
  
  Description: "service==poor & food==delicious => tip=average (1)"  
  Antecedent: [1 2]  
  Consequent: 2  
  Weight: 1  
  Connection: 1
```


Create Fuzzy Rule Using Numeric Description

Create a fuzzy rule using a numeric description. Specify that the rule has two input variables.

```
rule = fisrule([1 2 2 0.5 1],2)

rule =
  fisrule with properties:

    Description: "input1==mf1 & input2==mf2 => output1=mf2 (0.5)"
    Antecedent: [1 2]
    Consequent: 2
               Weight: 0.5000
    Connection: 1
```

Before using rule with a fuzzy system, update the rule Description property using the update function.

```
fis = readfis("tipper");
rule = update(rule,fis)

rule =
  fisrule with properties:

    Description: "service==poor & food==delicious => tip=average (0.5)"
    Antecedent: [1 2]
    Consequent: 2
               Weight: 0.5000
    Connection: 1
```

Input Arguments

ruleIn — Fuzzy rule

fisrule object | array of fisrule objects

Fuzzy rule, specified as a fisrule object or an array of fisrule objects. If ruleIn was created using a:

- Text description, its Antecedent and Consequent properties are updated using the input and output membership function indices in fis that correspond to the membership function names in the Description property of ruleIn
- Numeric description, its Description property is updated using the input and output membership function names in fis that correspond to the membership function indices in the Antecedent and Consequent properties of ruleIn

If you specify ruleIn as an array of fisrule objects, then all of the rules are updated accordingly.

fis — Fuzzy inference system

mamfis object | sugfis object | mamfistype2 object | sugfistype2 object

Fuzzy inference system, specified as one of the following:

- mamfis object — Mamdani fuzzy inference system

- `sugfis` object — Sugeno fuzzy inference system
- `mamfistype2` object — Type-2 Mamdani fuzzy inference system
- `sugfistype2` object — Type-2 Sugeno fuzzy inference system

Output Arguments

ruleOut — Fuzzy rule

`fisrule` object | array of `fisrule` objects

Fuzzy rule, returned as a `fisrule` object or an array of `fisrule` objects.

See Also

`fisrule`

Topics

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced in R2018b

writeFIS

Save fuzzy inference system to file

Syntax

```
writeFIS(fis, fileName)
```

```
writeFIS(fis)  
writeFIS(fis, fileName, "dialog")
```

Description

You can save a fuzzy inference system (FIS) in a `.fis` file using the `writeFIS` function. To load the saved file, use the `readfis` function.

Note Do not manually edit the contents of a `.fis` file. Doing so can produce unexpected results when loading the file using a function, such as `readfis` and `getCodeGenerationData`, or an app, such as **Fuzzy Logic Designer**.

`writeFIS(fis, fileName)` saves the fuzzy inference system `fis` to the current working folder using file name `fileName`.

`writeFIS(fis)` opens a dialog box for saving a FIS. In this dialog box, specify the name and location of the `.fis` file.

`writeFIS(fis, fileName, "dialog")` opens a dialog box for saving a FIS, setting the name of the file in the dialog box to `fileName`. In the dialog box, specify the location for the file.

Examples

Save Fuzzy Inference System to File

Create a fuzzy inference system, and add an input variable with membership functions.

```
fis = mamfis('Name', 'tipper');  
fis = addInput(fis, [0 10], 'Name', 'service');  
fis = addMF(fis, 'service', 'gaussmf', [1.5 0], 'Name', 'poor');  
fis = addMF(fis, 'service', 'gaussmf', [1.5 5], 'Name', 'good');  
fis = addMF(fis, 'service', 'gaussmf', [1.5 10], 'Name', 'excellent');
```

Save the fuzzy system in the current working folder in the file `myFile.fis`.

```
writeFIS(fis, 'myFile');
```

Input Arguments

fis — Fuzzy inference system

`mamfis` object | `sugfis` object | `mamfistype2` object | `sugfistype2` object

Fuzzy inference system, specified as one of the following:

- `mamfis` object — Mamdani fuzzy inference system
- `sugfis` object — Sugeno fuzzy inference system
- `mamfistype2` object — Type-2 Mamdani fuzzy inference system
- `sugfistype2` object — Type-2 Sugeno fuzzy inference system

fileName — File name

string | character vector

File name, specified as a string or character vector. If you do not specify the `.fis` extension in the file name, `writeFIS` adds the extension.

Compatibility Considerations

writefis is now **writeFIS**

Behavior changed in R2018b

`writefis` is now `writeFIS`. To update your code, change the function name from `writefis` to `writeFIS`. The syntaxes are equivalent.

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

See Also

`readfis`

Topics

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced in R2018b

zmf

Z-shaped membership function

Syntax

`y = zmf(x,params)`

Description

This function computes fuzzy membership values using a spline-based Z-shaped membership function. You can also compute this membership function using a `fismf` object. For more information, see “`fismf` Object” on page 8-275.

This membership function is related to the `smf` and `pimf` membership functions.

`y = zmf(x,params)` returns fuzzy membership values computed using the spline-based Z-shaped membership function given by:

$$f(x; a, b) = \begin{cases} 1, & x \leq a \\ 1 - 2\left(\frac{x-a}{b-a}\right)^2, & a \leq x \leq \frac{a+b}{2} \\ 2\left(\frac{x-b}{b-a}\right)^2, & \frac{a+b}{2} \leq x \leq b \\ 0 & x \geq b \end{cases}$$

To define the membership function parameters, specify `params` as the vector `[a b]`.

Membership values are computed for each input value in `x`.

Examples

Z-Shaped Membership Function

Specify input values across the universe of discourse.


```
x = 0:0.1:10;
```

Evaluate membership function for the input values.

```
y = zmf(x,[3 7]);
```

Plot the membership function.

```
plot(x,y)
title('zmf, P = [3 7]')
xlabel('x')
ylabel('Degree of Membership')
ylim([-0.05 1.05])
```



Input Arguments

x — Input values

scalar | vector

Input values for which to compute membership values, specified as a scalar or vector.

params — Membership function parameters

vector of length two

Membership function parameters, specified as the vector $[a \ b]$. Parameter a defines the *shoulder* of the membership function, and b defines its *foot*.

Output Arguments

y — Membership value

scalar | vector

Membership value returned as a scalar or a vector. The dimensions of y match the dimensions of x . Each element of y is the membership value computed for the corresponding element of x .

Alternative Functionality

fismf Object

You can create and evaluate a `fismf` object that implements the `zmf` membership function.

```
mf = fismf("zmf",P);  
Y = evalmf(mf,X);
```

Here, `X`, `P`, and `Y` correspond to the `x`, `params`, and `y` arguments of `zmf`, respectively.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using MATLAB® Coder™.

See Also

`fismf` | `fismftype2` | `psigmf` | `sigmf` | `gaussmf` | `gauss2mf` | `gbellmf` | `trimf` | `trapmf` | `linsmf` | `linzmf` | `pimf` | `smf` | `dsigmf`

Topics

"Membership Functions" on page 1-9

Introduced before R2006a

Objects

anfisOptions

Option set for `anfis` function

Description

Use an `anfisOptions` object to specify options for tuning fuzzy systems using the `anfis` function. You can specify options such as the initial FIS structure to tune and number of training epochs.

Creation

Syntax

```
opt = anfisOptions
opt = anfisOptions(Name,Value)
```

Description

`opt = anfisOptions` creates a default option set for tuning a Sugeno fuzzy inference system using `anfis`. Use dot notation to modify this option set for your specific application. Any options that you do not modify retain their default values.

`opt = anfisOptions(Name,Value)` sets properties on page 9-2 using one or more name-value arguments. Enclose the property name in quotes. For example, "EpochNumber", 50 sets the number of training epochs to 50.

Properties

InitialFIS — Initial FIS structure

2 (default) | positive integer greater than 1 | vector of positive integers | FIS structure

Initial FIS structure to tune, specified as one of the following values.

- Positive integer greater than 1 specifying the number of membership functions for all input variables. `anfis` generates an initial FIS structure with the specified number of membership functions using `genfis` with grid partitioning.
- Vector of positive integers with length equal to the number of input variables specifying the number of membership functions for each input variable. `anfis` generates an initial FIS structure with the specified numbers of membership functions using `genfis` with grid partitioning.
- FIS structure generated using `genfis` command with grid partitioning or subtractive clustering. The specified system must have the following properties:
 - Single output, obtained using weighted average defuzzification.
 - First or zeroth order Sugeno-type system; that is, all output membership functions must be the same type and be either 'linear' or 'constant'.
 - No rule sharing. Different rules cannot use the same output membership function; that is, the number of output membership functions must equal the number of rules.

- Unity weight for each rule.
- No custom membership functions or defuzzification methods.

EpochNumber — Maximum number of training epochs

10 (default) | positive integer

Maximum number of training epochs, specified as a positive integer. The training process stops when it reaches the maximum number of training epochs.

ErrorGoal — Training error goal

0 (default) | scalar

Training error goal, specified as a scalar. The training process stops when the training error is less than or equal to `ErrorGoal`.

InitialStepSize — Initial training step size

0.01 (default) | positive scalar

Initial training step size, specified as a positive scalar.

The `anfis` training algorithm tunes the FIS parameters using gradient descent optimization methods. The training step size is the magnitude of each gradient transition in the parameter space. Typically, you can increase the rate of convergence of the training algorithm by increasing the step size. During optimization, `anfis` automatically updates the step size using `StepSizeIncreaseRate` and `StepSizeDecreaseRate`.

Generally, the step-size profile during training is a curve that increases initially, reaches some maximum, and then decreases for the remainder of the training. To achieve this ideal step-size profile, adjust the initial step-size and the increase and decrease rates (`opt.StepSizeDecreaseRate`, `opt.StepSizeIncreaseRate`).

StepSizeDecreaseRate — Step-size decrease rate

0.9 (default) | positive scalar less than 1

Step-size decrease rate, specified as a positive scalar less than 1. If the training error undergoes two consecutive combinations of an increase followed by a decrease, then `anfis` scales the step size by the decrease rate.

StepSizeIncreaseRate — Step-size increase rate

1.1 (default) | scalar greater than 1

Step-size increase rate, specified as a scalar greater than 1. If the training error decreases for four consecutive epochs, then `anfis` scales the step size by the increase rate.

DisplayANFISInformation — Flag for showing ANFIS information

1 (default) | 0

Flag for showing ANFIS information at the start of the training process, specified as one of the following values.

- 1 — Display the following information about the ANFIS system and training data:
 - Number of nodes in the ANFIS system
 - Number of linear parameters to tune

- Number of nonlinear parameters to tune
- Total number of parameters to tune
- Number of training data pairs
- Number of checking data pairs
- Number of fuzzy rules
- 0 — Do not display the information.

DisplayErrorValues — Flag for showing training error values

1 (default) | 0

Flag for showing training error values after each training epoch, specified as one of the following values.

- 1 — Display the training error.
- 0 — Do not display the training error.

DisplayStepSize — Flag for showing step size

1 (default) | 0

Flag for showing step size whenever the step size changes, specified as one of the following values.

- 1 — Display the step size.
- 0 — Do not display the step size.

DisplayFinalResults — Flag for displaying final results

1 (default) | 0

Flag for displaying final results after training, specified as one of the following values.

- 1 — Display the results.
- 0 — Do not display the results.

ValidationData — Validation data

[] (default) | array

Validation data for preventing overfitting to the training data, specified as an array. For a fuzzy system with N inputs, specify `ValidationData` as an array with $N+1$ columns. The first N columns contain input data and the final column contains output data. Each row of `ValidationData` contains one data point.

At each training epoch, the training algorithm validates the FIS using the validation data.

Generally, validation data should fully represent the features of the data the FIS is intended to model, while also being sufficiently different from the training data to test training generalization.

OptimizationMethod — Optimization method

1 (default) | 0

Optimization method used in membership function parameter training, specified as one of the following values.

- 1 — Use a hybrid method, which uses a combination of backpropagation to compute input membership function parameters, and least squares estimation to compute output membership function parameters.
- 0 — Use backpropagation gradient descent to compute all parameters.

Object Functions

`anfis` Tune Sugeno-type fuzzy inference system using training data

Examples

Create Option Set for ANFIS Training

Create a default option set.

```
opt = anfisOptions;
```

Specify training options using dot notation. For example, specify the following options:

- Initial FIS with 4 membership functions for each input variable
- Maximum number of training epochs equal to 30.

```
opt.InitialFIS = 4;  
opt.EPOCHNumber = 30;
```

You can also specify options when creating the option set using one or more `Name, Value` pair arguments.

```
opt2 = anfisOptions('InitialFIS',4, 'EpochNumber',30);
```

See Also

`anfis` | `genfis`

Introduced in R2017a

ClauseParameters

Parameter settings for rule clauses

Description

A `ClauseParameters` object contains tunable settings for either the antecedent or consequent of a fuzzy rule.

Creation

Create a `ClauseParameters` object using the `getTunableSettings` function. The third output of `getTunableSettings` contains `RuleSettings` objects. The `Antecedent` and `Consequent` properties of each `RuleSettings` object are `ClauseParameter` objects for specifying the tunable settings of the corresponding rule.

Properties

Free — Clause parameter values available for tuning

1 | 0 | array of logical values

Clause parameter values available for tuning, specified as a logical 1 or 0, or an array of logical values. To apply different settings to each clause parameter, specify an array of logical values. To apply the same setting to all clause parameter values, specify a scalar logical value.

When the `ClauseParameters` object represents a rule antecedent, the clause parameter values are the membership functions corresponding to each input variable.

When the `ClauseParameters` object represents a rule consequent, the clause parameter values are the membership functions corresponding to each output variable.

AllowNot — Flag indicating whether to allow NOT logic in rule clauses

1 | 0 | array of logical values

Flag indicating whether to allow NOT logic in rule clauses, specified as a logical 1 or 0, or an array of logical values. To apply different settings to each clause parameter, specify an array of logical values. To apply the same setting to all clause parameter values, specify a scalar logical value.

AllowEmpty — Flag indicating whether to allow ignoring inputs and outputs in rule clauses

1 | 0 | array of logical values

Flag indicating whether to allow ignoring inputs and outputs in rule clauses, specified as a logical 1 or 0, or an array of logical values. To apply different settings to each clause parameter, specify an array of logical values. To apply the same setting to all clause parameter values, specify a scalar logical value.

Examples

Obtain Tunable Settings of Rules from FIS

Create two fuzzy inference systems, and define the connection between the two.

```

fis1 = mamfis('Name','fis1','NumInputs',2,'NumOutputs',1);
fis2 = sugfis('Name','fis2','NumInputs',2,'NumOutputs',1);
con = ["fis1/output1" "fis2/input1"];

```

Create a tree of fuzzy inference systems.

```
tree = fistree([fis1 fis2],con);
```

Obtain the tunable settings of rules of the fuzzy inference system.

```
[~,~,rule] = getTunableSettings(tree)
```

```

rule=18x1 object
  16x1 RuleSettings array with properties:

```

```

  Index
  Antecedent
  Consequent
  FISName
  :

```

You can use dot notation to specify the tunable settings of rules.

For the first rule, do not tune input 1 membership function index and do not ignore output 1 membership function index.

```

rule(1).Antecedent.Free(1) = false;
rule(1).Consequent.AllowEmpty(1) = false;

```

For the second rule, allow NOT logic for input 2 membership function index.

```
rule(2).Antecedent.AllowNot(2) = true;
```

See Also

[getTunableSettings](#) | [RuleSettings](#) | [VariableSettings](#)

Introduced in R2019a

evalfisOptions

Option set for evalfis function

Description

Use an evalfisOptions object to specify options for the evalfis function.

Creation

Syntax

```
opt = evalfisOptions  
opt = evalfisOptions(Name,Value)
```

Description

opt = evalfisOptions creates an option set for the evalfis function with default options. To modify the properties of this option set, use dot notation.

opt = evalfisOptions(Name,Value) sets properties using name-value pairs. For example, evalfisOptions('NumSamplePoints',51) creates an option set and sets the number of output fuzzy set samples to 51. You can specify multiple name-value pairs. Enclose each property name in single quotes.

Properties

NumSamplePoints — Number of sample points in output fuzzy sets

101 (default) | integer greater than 1

Number of sample points in output fuzzy sets, specified as an integer greater than 1.

To reduce memory usage while evaluating a Mamdani FIS, specify fewer samples. Doing so sacrifices the accuracy of the defuzzified output value.

Reducing the number of samples can make the output area for defuzzification zero. In this case, the defuzzified output value is the midpoint of the output variable range.

Note evalfis ignores this property when evaluating a Sugeno FIS.

OutOfRangeInputValueMessage — Diagnostic message behavior when an input is out of range

"warning" (default) | "error" | "none"

Diagnostic message behavior when an input is out of range, specified as one of the following:

- "warning" — Report the diagnostic message as a warning.
- "error" — Report the diagnostic message as an error.
- "none" — Do not report the diagnostic message.

When an input value is out of range, corresponding rules in the fuzzy system can have unexpected firing strengths.

NoRuleFiredMessage — Diagnostic message behavior when no rules fire

"warning" (default) | "error" | "none"

Diagnostic message behavior when no rules fire, specified as one of the following:

- "warning" — Report the diagnostic message as a warning.
- "error" — Report the diagnostic message as an error.
- "none" — Do not report the diagnostic message.

When NoRuleFiredMessage is "warning" or "none" and no rules fire for a given output, the defuzzified output value is set to its mean range value.

EmptyOutputFuzzySetMessage — Diagnostic message behavior when an output fuzzy set is empty

"warning" (default) | "error" | "none"

Diagnostic message behavior when an output fuzzy set is empty, specified as one of the following:

- "warning" — Report the diagnostic message as a warning.
- "error" — Report the diagnostic message as an error.
- "none" — Do not report the diagnostic message.

When EmptyOutputFuzzySetMessage is "warning" or "none" and an output fuzzy set is empty, the defuzzified value for the corresponding output is set to its mean range value.

This diagnostic message applies only to Mamdani systems.

Object Functions

evalfis Evaluate fuzzy inference system

Examples

Create Option Set for Evaluating FIS

Create option set object, specifying the number of sample points for output fuzzy sets.

```
options = evalfisOptions('NumSamplePoints',51)
```

```
options =
  EvalFISOptions with properties:
      NumSamplePoints: 51
  OutOfRangeInputValueMessage: "warning"
      NoRuleFiredMessage: "warning"
```

```
EmptyOutputFuzzySetMessage: "warning"
```

Alternatively, create a default option set, and configure properties using dot notation.

```
options = evalfisOptions;  
options.NumSamplePoints = 51;
```

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using MATLAB® Coder™.

Usage notes and limitations:

- When used for code generation, an `evalfisOptions` object stores its `OutOfRangeInputValueMessage`, `NoRuleFiredMessage`, and `EmptyOutputFuzzySetMessage` properties as character vectors rather than strings.
- When evaluating a fuzzy inference system in Simulink, it is recommended to not use `evalfis` or `evalfisOptions` within a MATLAB Function block. Instead, evaluate your fuzzy inference system using the Fuzzy Logic Controller block.

See Also

Functions

`evalfis`

Introduced in R2018a

fismf

Fuzzy membership function

Description

Use a `fismf` object to represent a type-1 fuzzy membership function. For each input and output variable in a fuzzy inference system (FIS), one or more membership functions define the possible linguistic sets for that variable. For more information on membership functions, see “Foundations of Fuzzy Logic” on page 1-7.

Creation

Syntax

```
mf = fismf
mf = fismf(type,parameters)
mf = fismf('Name',name)
mf = fismf(type,parameters,"Name",name)
```

Description

`mf = fismf` creates a fuzzy membership function (MF) with default type, parameters, and name. To change the membership function properties, use dot notation.

`mf = fismf(type,parameters)` sets the `Type` and `Parameters` properties.

`mf = fismf('Name',name)` sets the `Name` property.

`mf = fismf(type,parameters,"Name",name)` sets the `Type`, `Parameters`, and `Name` properties.

Properties

Name — Membership function name

"mf" (default) | string | character vector

Membership function name, specified as a string or character vector.

Type — Membership function type

"trimf" (default) | string | character vector | function handle

Membership function type, specified as a string or character vector that contains the name of a function in the current working folder or on the MATLAB path. You can also specify a handle to such a function. When you specify `Type`, you must also specify `Parameters`.

This table describes the values that you can specify for `Type`.

Membership Function Type	Description	For More Information
"gbellmf"	Generalized bell-shaped membership function	gbellmf
"gaussmf"	Gaussian membership function	gaussmf
"gauss2mf"	Gaussian combination membership function	gauss2mf
"trimf"	Triangular membership function	trimf
"trapmf"	Trapezoidal membership function	trapmf
"linsmf"	Linear s-shaped saturation membership function	linsmf
"linzmf"	Linear z-shaped saturation membership function	linzmf
"sigmf"	Sigmoidal membership function	sigmf
"dsigmf"	Difference between two sigmoidal membership functions	dsigmf
"psigmf"	Product of two sigmoidal membership functions	psigmf
"zmf"	Z-shaped membership function	zmf
"pimf"	Pi-shaped membership function	pimf
"smf"	S-shaped membership function	smf
"constant"	Constant membership function for Sugeno output membership functions	"Sugeno Fuzzy Inference Systems" on page 2-3
"linear"	Linear membership function for Sugeno output membership functions	
String or character vector	Name of a custom membership function in the current working folder or on the MATLAB path. Custom output membership functions are not supported for Sugeno systems.	"Build Fuzzy Systems Using Custom Functions" on page 2-40
Function handle	Handle to a custom membership function in the current working folder or on the MATLAB path. Custom output membership functions are not supported for Sugeno systems.	

Note When you change Type using dot notation, the values in Parameters are automatically converted for the new membership function type.

Parameters — Membership function parameters

[0 0.5 1] (default) | vector

Membership function parameters, specified as a vector. The length of the parameter vector depends on the membership function type. When you specify Parameters, you must also specify Type.

Object Functions

evalmf Evaluate fuzzy membership function

Examples

Create Membership Function

Create fuzzy membership function with default settings.

```
mf = fismf;
```

To modify the membership function settings, use dot notation. For example, specify a Gaussian membership function with a standard deviation of 2 and a mean of 10.

```
mf.Type = "gaussmf";  
mf.Parameters = [2 10];
```

Create Membership Function with Specified Parameters

Create a trapezoidal membership function with specified parameters.

```
mf = fismf("trapmf",[10 15 20 25]);
```

Create Membership Function with Specified Name

Create a membership function with the name "large".

```
mf = fismf("Name","large");
```

See Also

mamfis | sugfis | fisvar | fisrule

Topics

"Build Fuzzy Systems at the Command Line" on page 2-31

Introduced in R2018b


fismftype2

Interval type-2 fuzzy membership function

Description

Use a `fismftype2` object to represent an interval type-2 fuzzy membership function (MF), which introduce additional uncertainty into a fuzzy inference system.

An interval type-2 membership function is represented by an upper and a lower membership function. The values of the upper membership function are always greater than or equal to the corresponding lower membership function values. The area enclosed by these membership functions is the footprint of uncertainty (FOU). For example, the following plot shows three type-2 membership functions for a given input variable.



For more information on type-2 membership functions, see “Type-2 Fuzzy Inference Systems” on page 2-7.

Creation

Syntax

```
mf = fismftype2
mf = fismftype2(type,upperParameters)
mf = fismftype2( ____,Name,Value)
```

Description

`mf = fismftype2` creates a type-2 fuzzy membership function with default name, type, upper MF parameters, and lower MF configuration. To change the membership function properties, use dot notation.

`mf = fismftype2(type,upperParameters)` sets the `Type` and `UpperParameters` properties of the membership function.

`mf = fismftype2(____,Name,Value)` sets the `Name`, `LowerScale`, or `LowerLag` properties of the membership function using one or more name-value pair arguments for any of the other syntaxes.

Properties

Name — Membership function name

"mf" (default) | string | character vector

Membership function name, specified as a string or character vector.

Type — Membership function type

"trimf" (default) | string | character vector | function handle

Membership function type for both the upper and lower membership function, specified as a string or character vector that contains the name of a function in the current working folder or on the MATLAB path. You can also specify a handle to such a function. When you specify `Type`, you must also specify `UpperParameters`.

This table describes the values that you can specify for `Type`.

Membership Function Type	Description	For More Information
"gbellmf"	Generalized bell-shaped membership function	gbellmf
"gaussmf"	Gaussian membership function	gaussmf
"gauss2mf"	Gaussian combination membership function	gauss2mf
"trimf"	Triangular membership function	trimf
"trapmf"	Trapezoidal membership function	trapmf
"linsmf"	Linear s-shaped saturation membership function	linsmf

Membership Function Type	Description	For More Information
"linzmf"	Linear z-shaped saturation membership function	linzmf
"sigmf"	Sigmoidal membership function	sigmf
"dsigmoidf"	Difference between two sigmoidal membership functions	dsigmoidf
"psigmoidf"	Product of two sigmoidal membership functions	psigmoidf
"zmf"	Z-shaped membership function	zmf
"pimf"	Pi-shaped membership function	pimf
"smf"	S-shaped membership function	smf
String or character vector	Name of a custom membership function in the current working folder or on the MATLAB path. Custom output membership functions are not supported for Sugeno systems.	"Build Fuzzy Systems Using Custom Functions" on page 2-40
Function handle	Handle to a custom membership function in the current working folder or on the MATLAB path. Custom output membership functions are not supported for Sugeno systems.	

Note When you change Type using dot notation, the values in Parameters are automatically converted for the new membership function type.

UpperParameters — Upper membership function parameters

[0 0.5 1] (default) | vector

Upper membership function parameters, specified as a vector. The length of the parameter vector depends on the membership function type. When you specify Parameters, you must also specify Type.

LowerScale — Lower membership function scaling factor

1 (default) | positive scalar less than or equal to 1

Lower membership function scaling factor, specified as a positive scalar less than or equal to 1. Use LowerScale to define the maximum value of the lower membership function.

Depending on the value of LowerLag, the actual maximum lower membership function value can be less than LowerScale.

LowerLag — Lower membership function delay factor

scalar value between 0 and 1 | vector of length 2

Lower membership function delay factor, specified as a scalar value or a vector of length two. You can specify lag values between 0 and 1, inclusive.

The following membership function types support only a scalar LowerLag value:

- Symmetric MFs — `gaussmf` and `gbellmf`
- One-sided MFs — `sigmf`, `smf`, and `zmf`

All other built-in membership functions support either a scalar or vector `LowerLag` value. For these membership functions, when you specify a:

- Scalar value, the same lag value is used for both the left and right side of the membership function.
- Vector value, you can define different lag values for the left and right sides of the membership function.

The lag value defines the point at which the lower membership function value starts increasing from zero based on the value of the upper membership function. For example, a lag value of `0.1` indicates that the lower membership function becomes positive when the upper membership function has a membership value of `0.1`.

By default, the lag value is `0.2`. However, for some membership function types and upper membership function parameters, the software is unable to set a lower lag value to `0.2`. In such a case, the default lag value is set to a different valid value..

When the lag value is zero, the lower membership function starts increasing at the same point as the upper membership function.

Some membership function types restrict the maximum lag value. For example, `LowerLag` must be less than 1 for the `gaussmf`, `gauss2mf`, `gbellmf`, `sigmf`, `dsigmoid`, and `psigmoid` membership functions.

Object Functions

`evalmf` Evaluate fuzzy membership function

Examples

Create Type-2 Membership Function

Create type-2 membership function with default settings.

```
mf = fismftype2;
```

To modify the membership function settings, use dot notation. For example, specify a Gaussian upper membership function with a standard deviation of 2 and a mean of 10.

```
mf.Type = "gaussmf";
mf.UpperParameters = [2 10];
```

Specify the maximum lower membership function value as `0.8`.

```
mf.LowerScale = 0.8;
```

Configure the lower membership function to start increasing when the upper membership function reaches `0.3`.

```
mf.LowerLag = 0.3;
```

Create Type-2 Membership Function with Specified Upper MF Parameters

Create a trapezoidal type-2 membership function with specified upper MF parameters.

```
mf = fismftype2("trapmf",[3 4 6 7])  
  
mf =  
    fismftype2 with properties:  
  
                Type: "trapmf"  
    UpperParameters: [3 4 6 7]  
        LowerScale: 1  
        LowerLag: [0.2000 0.2000]  
                Name: "mf"
```

By default, the lower membership function has a maximum value of 1 and starts increasing when the upper MF is 0.2.

Configure Lower MF Parameters

Create a triangular type-2 membership function, specifying a maximum lower MF value of 0.9 and a membership function lag of 0.1.

```
mf = fismftype2("trimf",[1 2 3], 'LowerScale',0.9, 'LowerLag',0.1);
```

See Also

mamfistype2 | sugfistype2 | fisvar | fisrule | fismf

Topics

"Build Fuzzy Systems at the Command Line" on page 2-31

"Type-2 Fuzzy Inference Systems" on page 2-7

Introduced in R2019b

fisrule

Fuzzy rule

Description

Use `fisrule` objects to represent fuzzy if-then rules that relate input membership function conditions to corresponding output membership functions. The *if* portion of a fuzzy rule is the *antecedent*, which specifies the membership function for each input variable. The *then* portion of a fuzzy rule is the *consequent*, which specifies the membership function for each output variable. For more information on membership functions and fuzzy rules, see “Foundations of Fuzzy Logic” on page 1-7.

Creation

To create fuzzy rule objects, use the `fisrule` function. Using this function, you can create a single fuzzy rule or a vector of multiple fuzzy rules.

Syntax

```
rule = fisrule
rule = fisrule(ruleText)
rule = fisrule(ruleValues,numInputs)
```

Description

`rule = fisrule` creates a single fuzzy rule with the default description "input1==mf1 => output1=mf1".

`rule = fisrule(ruleText)` creates one or more fuzzy rules using the text descriptions in `ruleText`.

`rule = fisrule(ruleValues,numInputs)` creates one or more fuzzy rules using the numeric rule values in `ruleValues`. Specify the number of rule input variables using `numInputs`.

Input Arguments

ruleText — Text rule description

string | character vector | string array | character array

Text rule description, specified as one of the following:

- String or character vector specifying a single rule.

```
rule = "If service is poor or food is rancid then tip is cheap";
```

- String array, where each element corresponds to a rule.

```
ruleList = ["If service is poor or food is rancid then tip is cheap";
            "If service is good then tip is average";
            "If service is excellent or food is delicious then tip is generous"];
```

- Character array where each row corresponds to a rule.

```
rule1 = 'If service is poor or food is rancid then tip is cheap';
rule2 = 'If service is good then tip is average';
rule3 = 'If service is excellent or food is delicious then tip is generous';
ruleList = char(rule1,rule2,rule3);
```

For each rule, use one of the following rule text formats.

- Verbose — Linguistic expression in the following format, using the IF and THEN keywords:

```
"IF <antecedent> THEN <consequent> (<weight>)"
```

In <antecedent>, specify the membership function for each input variable using the IS or IS NOT keyword. Connect these conditions using the AND or OR keywords. If a rule does not use a given input variable, omit it from the antecedent.

In <consequent>, specify the condition for each output variable using the IS or IS NOT keyword, and separate these conditions using commas. The IS NOT keyword is not supported for Sugeno outputs. If a rule does not use a given output variable, omit it from the consequent.

Specify the weight using a positive numerical value.

```
"IF A IS a AND B IS NOT b THEN X IS x, Y IS NOT y (1)"
```

- Symbolic — Expression that uses the symbols in the following table instead of keywords. There is no symbol for the IF keyword.

Symbol	Keyword
==	IS (in rule antecedent)
~=	IS NOT
&	AND
	OR
=>	THEN
=	IS (in rule consequent)

For example, the following symbolic rule is equivalent to the previous verbose rule.

```
"A==a & B~=b => X=x, Y~=y (1)"
```

When you specify a rule using a text description, `fisrule` sets the `Description`, `Weight`, and `Connection` properties of the rule based on the description.

ruleValues — Numeric rule description

row vector | numeric array

Numeric rule description, specified as one of the following:

- Row vector to specify a single fuzzy rule
- Array, where each row of `ruleValues` specifies one rule

For each row, the numeric rule description has $M+N+2$ columns, where M is the number of input variables and N is the number of output variables. Each column contains the following information:

- The first M columns specify input membership function indices and correspond to the **Antecedent** property of the rule. To indicate a **NOT** condition, specify a negative value. If a rule does not use a given input, set the corresponding index to \emptyset . For each rule, at least one input membership function index must be nonzero.
- The next N columns specify output membership function indices and correspond to the **Consequent** property of the rule. To indicate a **NOT** condition for Mamdani systems, specify a negative value. **NOT** conditions are not supported for Sugeno outputs. If a rule does not use a given output, set the corresponding index to \emptyset . For each rule, at least one output membership function index must be nonzero.
- Column $M+N+1$ specifies the rule weight and corresponds to the **Weight** property of the rule.
- The final column specifies the antecedent fuzzy operator and corresponds to the **Connection** property of the rule.

When you specify a rule using `ruleValues`, `fisrule` sets the **Description** property using default variable and membership function names.

numInputs — Number of input variables

positive integer

Number of input variables for the rule, specified as a positive integer. If you specify the rule description using `ruleValues`, you must also specify the number of input variables. `fisrule` parses the rule antecedent values into the membership function indices for the input and output variables using `numInputs`.

Properties

Description — Text rule description

string | character vector

Text rule description, specified as a string or character vector. The rule description is stored as a symbolic expression no matter how you specify the rule. For example, if you specify the following verbose rule using `ruleText`:

```
"IF A IS a AND B IS NOT b THEN X IS x, Y IS NOT y (1)"
```

The stored rule is:

```
"A==a & B~=b => X=x, Y~=y (1)"
```

For more information on the verbose and symbolic rule formats, see the `ruleText` input argument.

When you specify a rule using `ruleValues`, `fisrule` sets the **Description** property using default variable and membership function names. Before using the rule in a fuzzy system, you must update the description to use the variable and membership function names from that fuzzy system using the `update` function.

Antecedent — Rule antecedent

numeric vector

Rule antecedent, specified as a numeric vector of length M , where M is the number of input variables. Each element of **Antecedent** contains one of the following values:

- Positive integer — The index of an input membership function, which represents an **IS** condition

- Negative integer — The negative of an input membership function, which represents an IS NOT condition
- 0 — A *don't care* condition, which means that the rule does not use the corresponding input variable

This value is set when you create a fuzzy rule using `ruleValues`. If you create a fuzzy rule using `ruleText`, before using the rule in a fuzzy system, you must populate the `Antecedent` property using the `update` function.

If you update the indices in the rule antecedent using dot notation, the `Description` property is not updated to reflect the changes. To update the rule description, use the `update` function.

Consequent — Rule consequent

numeric vector

Rule consequent, specified as a numeric vector of length N , where N is the number of output variables. Each element of `Consequent` contains one of the following values:

- Positive integer — The index of an output membership function, which represents an IS condition
- Negative integer — The negative of an output membership function, which represents an IS NOT condition
- 0 — A *don't care* condition, which means that the rule does not use the corresponding output variable

This value is set when you create a fuzzy rule using `ruleValues`. If you create a fuzzy rule using `ruleText`, before using the rule in a fuzzy system, you must populate the `Consequent` property using the `update` function.

If you update the indices in the rule consequent using dot notation, the `Description` property is not updated to reflect the changes. To update the rule description, use the `update` function.

Weight — Rule weight

1 (default) | positive numeric scalar

Rule weight, specified as a positive numeric scalar in the range [0 1].

If you update the rule weight using dot notation, the weight value in the `Description` property text is also updated.

Connection — Rule antecedent connection

1 | 2

Rule antecedent connection, specified as one of the following:

- 1 — Evaluate rule antecedents using the AND operator.
- 2 — Evaluate rule antecedents using the OR operator.

If you update the rule connection using dot notation, the antecedent operators in the `Description` property text are also updated.

Object Functions

`update` Update fuzzy rule using fuzzy inference system

Examples

Create Fuzzy Rule

Create a default fuzzy rule.

```
rule = fisrule

rule =
  fisrule with properties:

    Description: "input1==mf1 => output1=mf1 (1)"
    Antecedent: 1
    Consequent: 1
    Weight: 1
    Connection: 1
```

To modify the rule properties, use dot notation. For example, specify a rule weight of 0.5.

```
rule.Weight = 0.5;
```

Create Fuzzy Rule Using Text Description

Create a fuzzy rule using a verbose text description.

```
rule = fisrule("if service is poor and food is delicious then tip is average (1)");
```

Alternatively, you can specify the same rule using a symbolic text description.

```
rule = fisrule("service==poor & food==delicious => tip=average")

rule =
  fisrule with properties:

    Description: "service==poor & food==delicious => tip=average (1)"
    Antecedent: []
    Consequent: []
    Weight: 1
    Connection: 1
```

Before using `rule` with a fuzzy system, update the rule Antecedent and Consequent properties using the `update` function.

```
fis = readfis("tipper");
rule = update(rule, fis)

rule =
  fisrule with properties:

    Description: "service==poor & food==delicious => tip=average (1)"
    Antecedent: [1 2]
    Consequent: 2
    Weight: 1
```

```
Connection: 1
```

Create Fuzzy Rule Using Numeric Description

Create a fuzzy rule using a numeric description. Specify that the rule has two input variables.

```
rule = fisrule([1 2 2 0.5 1],2)

rule =
  fisrule with properties:

    Description: "input1==mf1 & input2==mf2 => output1=mf2 (0.5)"
    Antecedent: [1 2]
    Consequent: 2
    Weight: 0.5000
    Connection: 1
```

Before using `rule` with a fuzzy system, update the rule `Description` property using the `update` function.

```
fis = readfis("tipper");
rule = update(rule,fis)

rule =
  fisrule with properties:

    Description: "service==poor & food==delicious => tip=average (0.5)"
    Antecedent: [1 2]
    Consequent: 2
    Weight: 0.5000
    Connection: 1
```

Create Multiple Fuzzy Rules

Create a string array of text rule descriptions.

```
rules1 = ["if service is poor or food is rancid then tip is cheap (0.5)"...
         "if service is excellent and food is not rancid then tip is generous (0.75)"];
```

Create an array of fuzzy rules using these descriptions.

```
fuzzyRules1 = fisrule(rules1)

fuzzyRules1 =
  1x2 fisrule array with properties:

    Description
    Antecedent
    Consequent
    Weight
```


Connection

Details:

Description

```

1  "service==poor | food==rancid => tip=cheap (0.5)"
2  "service==excellent & food~=rancid => tip=generous (0.75)"

```

Alternatively, you can specify multiple rules using an array of numeric rule descriptions.

```

rules2 = [1 1 1 0.5 2;
          2 -1 3 0.75 1];
fuzzyRules2 = fisrule(rules2,2)

```

```

fuzzyRules2 =
  1x2 fisrule array with properties:

```

```

  Description
  Antecedent
  Consequent
  Weight
  Connection

```

Details:

Description

```

1  "input1==mf1 | input2==mf1 => output1=mf1 (0.5)"
2  "input1==mf2 & input2~=mf1 => output1=mf3 (0.75)"

```

See Also

mamfis | sugfis | mamfistype2 | sugfistype2 | fisvar | fismf

Topics

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced in R2018b

fistree

Network of connected fuzzy inference systems

Description

Use a `fistree` object to represent a tree of interconnected fuzzy inference systems.

Creation

Syntax

```
fisTree = fistree(fis,connections)
fisTree = fistree(___,Name,Value)
```

Description

`fisTree = fistree(fis,connections)` creates a network of interconnected fuzzy inference system objects, setting its `FIS` and `Connections` properties

`fisTree = fistree(___,Name,Value)` sets the `Name` or `DisableStructuralChecks` property of the FIS tree using name-value arguments. Specify these arguments after the arguments described in the previous syntax. For example, `fistree(___, 'Name', "mytree")` sets the name of the FIS tree to "mytree". You can specify both properties using two name-value arguments.

Properties

Name — FIS tree name

"fistreemodel" (default) | string | character vector

FIS tree name, specified as a string or character vector.

FIS — Fuzzy inference systems

array

This property is read-only.

Fuzzy inference systems, specified as an array of FIS objects. You can specify any combination of `mamfis`, `sugfis`, `mamfistype2`, and `sugfistype2` objects. Each fuzzy inference system in the `fis` array must have at least one input and one output for `fistree` construction. To evaluate a `fistree`, each fuzzy inference system must have at least one rule.

Connections — Connections between fuzzy inference systems


two-column string array

Connections between fuzzy inference systems, specified as a two-column string array. Each row represents a connection between two FIS objects. You can specify two types of connections.

- 1 Output-to-input connections — Specify a connection from the output of one FIS to the input of a different FIS.
- 2 Input-to-input connections — Specify a connection between two inputs so that they use the same input value.

To define a connection, specify the FIS name and variable name for both the source and destination of the connection. For example, ["fisFrom/out1" "fisTo/in1"] defines a connection from output out1 of FIS fisFrom to input in1 of FIS fisTo.

The following figure demonstrates the different connection types using three FIS objects, fis1, fis2, and fis3.



This FIS tree includes the following connections.

- ["fis1/output1" "fis3/input1"] — Connection from output output1 of fis1 to input input1 of fis3
- ["fis2/output1" "fis3/input2"] — Connection from output output1 of fis2 to input input2 of fis3
- ["fis1/input2" "fis2/input1"] — Connection from input input2 of fis1 to input input1 of fis2

Connections must satisfy the following conditions:

- 1 A fistree object must have at least one FIS input without any incoming connection and one FIS output without any outgoing connection.
- 2 A FIS input cannot have more than one incoming connection.
- 3 A FIS output can have more than one outgoing connection.

- 4 An input and output of the same FIS cannot be connected. In other words, you cannot create loops between connected FIS objects.
- 5 Symmetric connections between two inputs are not supported. For example, ["fis1/a" "fis2/b"; "fis2/b" "fis1/a"] is not supported. Instead, specify ["fis1/a" "fis2/b"] or ["fis2/b" "fis1/a"].
- 6 Self-input loops, such as ["fis1/a" "fis1/a"], are not supported.

Inputs — Inputs to FIS tree

string array

This property is read-only.

Inputs to the FIS tree, specified as an array of strings. Inputs are automatically determined using the specified connections of the `fistree` object. FIS inputs with no incoming connections are included in `Inputs`.

Update this property by updating the connections of the `fistree` object.

Outputs — Outputs of FIS tree

string array

Outputs of the FIS tree, specified as a string array. Outputs are automatically determined using the specified connections of the `fistree` object. FIS outputs without any outgoing connections are included in `Outputs`.

You can update this property after initial construction of the `fistree` object. You can remove an existing input or add additional intermediate outputs. `Outputs` must contain at least one output.

DisableStructuralChecks — Option for disabling structural checks

false (default) | true

Option for disabling structural checks when the FIS tree is updated after initial FIS creation, specified as one of the following values.

- `false` — Automatically update connections, inputs, and outputs. This option ensures that the FIS tree is always valid and can be evaluated.
- `true` — Do not automatically update connections, inputs, and outputs. In this case, the resulting FIS tree can be in an invalid state, which can cause an error during evaluation.

Enable this option to improve computational efficiency when you programmatically construct a FIS tree.

Object Functions

<code>evalfis</code>	Evaluate fuzzy inference system
<code>plotfis</code>	Display fuzzy inference system
<code>getTunableSettings</code>	Obtain tunable settings from fuzzy inference system
<code>getTunableValues</code>	Obtain values of tunable parameters from fuzzy inference system
<code>setTunableValues</code>	Specify tunable parameter values of a fuzzy inference system

Examples

Create Tree of Connected Fuzzy Inference Systems

Create a Mamdani fuzzy inference system and a Sugeno fuzzy inference system.

```

fis1 = mamfis('Name','fis1','NumInputs',2,'NumOutputs',1);
fis2 = sugfis('Name','fis2','NumInputs',2,'NumOutputs',1);

```

Define a connection from the output of fis1 to the first input of fis2.

```

con1 = ["fis1/output1" "fis2/input1"];

```

Create a FIS tree using the fuzzy inference systems and connection.

```

tree = fistree([fis1 fis2],con1);


```

Visualize the tree.

```

plotfis(tree)

```



Update Fuzzy Inference Systems in FIS Tree

Create a tree with two FISs and no connections.

```

fis1 = mamfis('Name','fis1','NumInputs',2,'NumOutputs',1);
fis2 = mamfis('Name','fis2','NumInputs',2,'NumOutputs',1);

```

```

fisT = fistree([fis1 fis2],[]);



```

Display the FIS tree configuration.

```

plotfis(fisT)

```



You can add a FIS to a FIS tree by appending a FIS object to the FIS property of the tree.

Add `fis3` to the FIS tree.


```
fis3 = mamfis('Name','fis3','NumInputs',2,'NumOutputs',1);  
fisT.FIS(end+1) = fis3;
```

Connect the outputs of `fis1` and `fis2` to the inputs of `fis3`.

```
fisT.Connections = [  
    "fis1/output1" "fis3/input1";  
    "fis2/output1" "fis3/input2"];
```

Display the updated FIS tree configuration.

```
plotfis(fisT)
```




Remove the first FIS (`fis1`) from the FIS tree.

```
fisT.FIS(1) = [];
```

Display the updated FIS tree configuration.

```
plotfis(fisT)
```



The corresponding connection to the first input of `fis3` is also removed.

Use Same Value for Multiple Inputs of FIS Tree

Create `fis1`, `fis2`, and `fis3`, each with two inputs and one output.

```
fis1 = mamfis('Name','fis1','NumInputs',2,'NumOutputs',1);  
fis2 = mamfis('Name','fis2','NumInputs',2,'NumOutputs',1);  
fis3 = mamfis('Name','fis3','NumInputs',2,'NumOutputs',1);
```

Create a connection between output 1 of `fis1` and input 1 of `fis3`.

```
con1 = ["fis1/output1" "fis3/input1"];
```

Create a connection between output 1 of `fis2` and input 2 of `fis3`.


```
con2 = ["fis2/output1" "fis3/input2"];
```

Create a connection between input 2 of `fis1` and input 1 of `fis2`.

```
con3 = ["fis1/input2" "fis2/input1"];
```

Create and display the FIS tree.

```
fuzzTree = fistree([fis1 fis2 fis3],[con1;con2;con3]);  
plotfis(fuzzTree)
```



Display the inputs of the FIS tree. These inputs correspond to all free inputs that do not have an incoming connection.

```
fuzzTree.Inputs
```

```
ans = 3×1 string
    "fis1/input1"
    "fis1/input2"
    "fis2/input2"
```

Evaluate the fuzzy tree. Specify values for input 1 of `fis1`, input 2 of `fis1`, and input 2 of `fis2`. The value for input 2 of `fis1` is also applied to input 1 of `fis2`.

```
output = evalfis(fuzzTree,[0.8 0.25 0.7]);
```

Update FIS Tree Outputs

Create two FIS objects, each with two inputs and one output.

```
fis1 = mamfis('Name','fis1','NumInputs',2,'NumOutputs',1);
fis2 = mamfis('Name','fis2','NumInputs',2,'NumOutputs',1);
```

Connect the output of `fis1` to the second input of `fis2`.

```
con = ["fis1/output1" "fis2/input2"];
```

Create the FIS tree.

```
fuzzTree = fistree([fis1 fis2],con);
```


Display outputs of the FIS tree. By default, the open FIS output from `fis2` is an output of the FIS tree.

```
fuzzTree.Outputs
```

```
ans =
    "fis2/output1"
```

Visualize the FIS tree.

```
plotfis(fuzzTree,Legend="on")
```



Add the output of `fis1` to the list of outputs.

```
fuzzTree.Outputs(end+1) = "fis1/output1";
```


Display the updated output list of the FIS tree.

```
fuzzTree.Outputs
```

```
ans = 2x1 string  
    "fis2/output1"  
    "fis1/output1"
```

Visualize the FIS tree. The added intermediate output is highlighted.

```
plotfis(fuzzTree, Legend="on")
```



Evaluate the FIS tree. The result contains the outputs from `fis2` and `fis1`.

```
evalfis(fuzzTree,[0.5 0.2 0.8])
```

```
ans = 1×2
```

```
    0.1579    0.1579
```

Remove the first output from the list.

```
fuzzTree.Outputs(1) = [];
```


Display the updated output list of the FIS tree.

```
fuzzTree.Outputs
```

```
ans =  
"fis1/output1"
```

Visualize the FIS tree without the removed output. The visualization indicates that the output of `fis2` is unused.

```
plotfis(fuzzTree,Legend="on")
```



Evaluate the FIS tree again. The result now contains the output of only `fis2`.

```
evalfis(fuzzTree,[0.5 0.2 0.8])
```

```
ans = 0.1579
```

Create Incremental FIS Tree

This example shows the construction of an incremental FIS tree. For more information on the types of fuzzy tree structures, see “Fuzzy Trees” on page 2-52.

Create fuzzy systems `fis1`, `fis2`, and `fis3`, each with two inputs and one output.

```
fis1 = mamfis('Name','fis1','NumInputs',2,'NumOutputs',1);
fis1.Inputs(1).Name = "color";
fis1.Inputs(2).Name = "doors";
fis2 = mamfis('Name','fis2','NumInputs',2,'NumOutputs',1);
fis2.Inputs(2).Name = "power";
fis3 = mamfis('Name','fis3','NumInputs',2,'NumOutputs',1);
fis3.Inputs(2).Name = "autopilot";
fis3.Outputs(1).Name = "prediction";
```

Create a connection between output 1 of `fis1` and input 1 of `fis2`.

```
con1 = ["fis1/output1" "fis2/input1"];
```

Create a connection between output 1 of `fis2` and input 1 of `fis3`.


```
con2 = ["fis2/output1" "fis3/input1"];
```

Create the FIS tree.

```
incTree = fistree([fis1 fis2 fis3],[con1;con2]);
```

Visualize the tree structure. At each level of the tree structure, an additional input is combined with the output of the previous level.

```
plotfis(incTree)
```



Create Aggregated FIS Tree

This example shows the construction of an aggregated FIS tree. For more information on the types of fuzzy tree structures, see “Fuzzy Trees” on page 2-52.

Create fuzzy systems `fis1`, `fis2`, and `fis3`, each with two inputs and one output.

```

fis1 = mamfis('Name','fis1','NumInputs',2,'NumOutputs',1);
fis1.Inputs(1).Name = "dist_obs";
fis1.Inputs(2).Name = "angle_obs";
fis2 = mamfis('Name','fis2','NumInputs',2,'NumOutputs',1);
fis2.Inputs(1).Name = "dist_tar";
fis2.Inputs(2).Name = "angle_tar";
fis3 = mamfis('Name','fis3','NumInputs',2,'NumOutputs',1);
fis3.Outputs(1).Name = "heading_robot";
  
```

Create a connection between output 1 of `fis1` and input 1 of `fis3`.

```
con1 = ["fis1/output1" "fis3/input1"];
```

Create a connection between output 1 of `fis2` and input 2 of `fis3`.


```
con2 = ["fis2/output1" "fis3/input2"];
```

Create the FIS tree.

```
aggTree = fistree([fis1 fis2 fis3],[con1;con2]);
```

Visualize the tree structure.

```
plotfis(aggTree)
```



Create Cascaded FIS Tree

This example shows the construction of a cascaded FIS tree. For more information on the types of fuzzy tree structures, see “Fuzzy Trees” on page 2-52.

Create fuzzy systems `fis1`, `fis2`, `fis3`, and `fis4`, each with two inputs and one output.

```

fis1 = mamfis('Name', 'fis1', 'NumInputs', 2, 'NumOutputs', 1);
fis1.Inputs(1).Name = "dist_obs";
fis1.Inputs(2).Name = "angle_obs";
fis2 = mamfis('Name', 'fis2', 'NumInputs', 2, 'NumOutputs', 1);
fis2.Inputs(1).Name = "dist_tar";
fis2.Inputs(2).Name = "angle_tar";
fis3 = mamfis('Name', 'fis3', 'NumInputs', 2, 'NumOutputs', 1);
fis4 = mamfis('Name', 'fis4', 'NumInputs', 2, 'NumOutputs', 1);
fis4.Inputs(2).Name = "preheading_robot";
fis4.Outputs(1).Name = "heading_robot";
  
```

Create a connection between output 1 of `fis1` and input 1 of `fis3`.

```
con1 = ["fis1/output1" "fis3/input1"];
```

Create a connection between output 1 of `fis2` and input 2 of `fis3`.

```
con2 = ["fis2/output1" "fis3/input2"];
```

Create a connection between output 1 of fis3 and input 1 of fis4.


```
con3 = ["fis3/output1" "fis4/input1"];
```

Create the FIS tree.

```
casTree = fistree([fis1 fis2 fis3 fis4],[con1;con2;con3]);
```

Visualize the tree structure.

```
plotfis(casTree)
```



Create and Evaluate Parallel FIS Tree

This example shows the construction of a parallel FIS tree. For more information on the types of fuzzy tree structures, see “Fuzzy Trees” on page 2-52.

Create fuzzy systems `fis1`, `fis2`, and `fis3`, each with two inputs and one output.



```
fis1 = mamfis('Name','fis1','NumInputs',2,'NumOutputs',1);
fis2 = mamfis('Name','fis2','NumInputs',2,'NumOutputs',1);
```

Create the FIS tree such that the FIS objects are in parallel; that is, the tree contains no interconnections and all the FIS outputs are FIS tree outputs.

```
parTree = fistree([fis1 fis2],[]);
```

Visualize the tree.

```
plotfis(parTree)
```



Evaluate the FIS tree.

```
output = evalfis(parTree,[0.1 0.3 0.8 0.4]);
```

Generate the final output by summing the FIS tree outputs.

```
finalOutput = sum(output);
```

See Also

`mamfis` | `sugfis` | `mamfistype2` | `sugfistype2` | `tunefis`

Topics

“Fuzzy Trees” on page 2-52

“Mamdani and Sugeno Fuzzy Inference Systems” on page 2-2

Introduced in R2019a

fisvar

Fuzzy variable

Description

Use `fisvar` objects to represent the input and output variables in a fuzzy inference system (FIS). For more information on creating fuzzy inference systems, see `mamfis`, `sugfis`, `mamfistype2`, and `sugfistype2`.

Creation

Syntax

```
var = fisvar
var = fisvar(range)
var = fisvar('Name',name)
var = fisvar(range,'Name',name)
```

Description

`var = fisvar` creates a fuzzy variable with a default name, default range, and no membership functions. To change the variable properties, use dot notation.

`var = fisvar(range)` sets the Range property.

`var = fisvar('Name',name)` sets the Name property.

`var = fisvar(range,'Name',name)` sets both the Range and Name properties.

Properties

Name — Variable name

"var" (default) | string | character vector

Variable name, specified as a string or character vector.

Range — Variable range

[0 1] (default) | two-element vector

Variable range, specified as a two-element element vector where the first element is less than the second element. The first element specifies the lower bound of the range, and the second element specifies the upper bound of the range.

MembershipFunctions — Membership functions

[] (default) | vector of `fismf` objects | vector of `fismftype2` objects

Membership functions, specified as a vector of `fismf` or `fismftype2` objects. To add membership functions to a fuzzy variable:

- Use the `addMF` function.
- Create a vector of `fismf` objects, and assign it to `MembershipFunctions`.
- Create a vector of `fismftype2` objects, and assign it to `MembershipFunctions`.

You can modify the properties of the membership functions using dot notation.

Object Functions

`addMF` Add membership function to fuzzy variable

`removeMF` Remove membership function from fuzzy variable

Examples

Create Fuzzy Variable

Create a fuzzy variable with default properties.

```
var = fisvar;
```

To modify the properties of a `fisvar` object, use dot notation. For example, specify the range of the fuzzy variable to be from -5 to 5.

```
var.Range = [-5 5];
```

Create Fuzzy Variable with Specified Range

Create a fuzzy variable with an input range from -10 to 10.

```
var = fisvar([-10 10]);
```

Create Fuzzy Variable with Specified Name

Create a fuzzy variable with the name "speed".

```
var = fisvar("Name", "speed");
```

Add Membership Function to Fuzzy Variable

Create a fuzzy variable with a specified range.

```
var = fisvar([0 1]);
```

Add a membership function to the variable, specifying a trapezoidal membership function, and set the membership function parameters.

```
var = addMF(var, "trapmf", [-0.5 0 0.2 0.4]);
```

You can also specify the name of your membership when you add it to a fuzzy variable. For example, add a membership function called "large".

```
var = addMF(var,"trapmf",[0.6 0.8 1 1.5],'Name',"large");
```

View the membership functions.

```
var.MembershipFunctions
```

```
ans =
  1x2 fismf array with properties:
```

```
    Type
Parameters
    Name
```

Details:

	Name	Type	Parameters			
1	"mf1"	"trapmf"	-0.5	0	0.2	0.4
2	"large"	"trapmf"	0.6	0.8	1	1.5

Alternatively, you can add a default membership function to a fuzzy variable and set its parameters using dot notation.

```
var = fisvar([0 1]);
var = addMF(var);
var.MembershipFunctions(1).Type = "trapmf";
var.MembershipFunctions(1).Parameters = [-0.5 0 0.2 0.4];
```

Add Type-2 Membership Function to Fuzzy Variable

Create a fuzzy variable with a specified range. By default, this variable has no membership functions.

```
var = fisvar([0 9]);
```

To add a type-2 membership function to a variable with no existing membership functions, specify either a `LowerLag` or `LowerScale` value for the membership function. For example specify a lower scale value.

```
var = addMF(var,"trimf",[0 3 6],'LowerScale',1);
```

Once a variable contains a type-2 membership function, you can add additional type-2 membership functions without specifying one of these parameters.

```
var = addMF(var,"trimf",[3 6 9]);
```

View the membership functions.

```
var.MembershipFunctions
```

```
ans =
  1x2 fismftype2 array with properties:
```

Type
UpperParameters
LowerScale
LowerLag
Name

Details:

	Name	Type	Upper Parameters			Lower Scale	Lower Lag	
1	"mf1"	"trimf"	0	3	6	1	0.2	0.2
2	"mf2"	"trimf"	3	6	9	1	0.2	0.2

See Also

mamfis | sugfis | mamfistype2 | sugfistype2 | fisrule | fismf | fismftype2

Topics

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced in R2018b

gensurfOptions

Option set for gensurf function

Description

Use a `gensurfOptions` object to specify options for creating a surface plot using `gensurf`. You can specify options such as the inputs to plot the output against and the number of grid points to plot.

Creation

Syntax

```
opt = gensurfOptions
opt = gensurfOptions(Name,Value)
```

Description

`opt = gensurfOptions` creates a default option set for generating a fuzzy inference system output surface using `gensurf`. Use dot notation to modify this option set for your specific application. Any options that you do not modify retain their default values.

`opt = gensurfOptions(Name,Value)` sets properties on page 9-45 using one or more name-value arguments. Enclose the property name in quotes. For example, `"NumGridPoints",30` sets the number of grid points to 30.

Properties

InputIndex — Indices of input variables

'auto' (default) | positive integer less than or equal to the number of inputs | two-element vector of positive integers

Indices of input variables to plot the output against, specified as the comma-separated pair consisting of 'InputIndex' and one of the following:

- Positive integer less than or equal to the number of inputs — Plot the output against a single input using a 2-D plot.
- Two-element vector of positive integers — Plot the output against two input variables using a 3-D surface plot.

When `InputIndex` is 'auto', `gensurf` uses the first two input variables by default.

OutputIndex — Index of output variable

'auto' (default) | positive integer less than or equal to the number of outputs

Index of output variable to plot, specified as the comma-separated pair consisting of 'OutputIndex' and a positive integer less than or equal to the number of outputs.

When `OutputIndex` is 'auto', `gensurf` uses the first output variable by default.

NumGridPoints — Number of grid points to plot

15 (default) | integer greater than 1 | two-element vector of integers greater than 1

Number of grid points to plot, specified as the comma-separated pair consisting of 'NumGridPoints' and one of the following:

- Integer greater than 1 — Specify the number of grid points when using a single input variable, or the same number of grid points for both inputs when using two inputs variables.
- Two-element vector of integers greater than 1 — Specify a different number of grid points for each input variable.

If you specify `InputIndex` as an integer and `NumGridPoints` as a vector, then `gensurf` uses the first element of `NumGridPoints` as the number of grid points for the specified input variable.

To plot a smoother surface, increase the number of grid points.

ReferenceInputs — Reference values for input variables

'auto' (default) | vector

Reference values for input variables not shown in the surface plot, specified as the comma-separated pair consisting of 'ReferenceInputs' and a vector with length equal to the number of FIS inputs. Specify NaN for the inputs specified in `InputIndex`.

When `ReferenceInputs` is 'auto', `gensurf` uses the midpoint of the range of each unused variable as a reference value.

NumSamplePoints — Number of sample points

101 (default) | integer greater than 1

Number of sample points to use when evaluating membership functions over the output variable range, specified as the comma-separated pair consisting of 'NumSamplePoints' and an integer greater than 1. For more information on membership function evaluation, see `evalfis`.

Note `NumSamplePoints` is not used by Sugeno-type systems.

Object Functions`gensurf` Generate fuzzy inference system output surface**Examples****Specify Options for Generating Output Surface**

Create a default `gensurfOptions` option set.

```
opt = gensurfOptions;
```

Specify options using dot notation. For example, for a two-input, three-output fuzzy system, specify options to:

- Plot the surface for the second output against the values of the first and third inputs.

- Specify a reference value of 0.25 for the second input variable.

```
opt.OutputIndex = 2;  
opt.InputIndex = [1 3];  
opt.ReferenceInputs = [NaN 0.25 NaN];
```

Any values you do not specify remain at their default values.

You can also specify one or more options when creating the option set. For example, create an option set, specifying 25 grid points for both plotted input variables:

```
opt2 = gensurfOptions('NumGridPoints',25);
```

See Also

gensurf | evalfis

Introduced in R2017a

mamfis

Mamdani fuzzy inference system

Description

Use a `mamfis` object to represent a type-1 Mamdani fuzzy inference system (FIS).

As an alternative to a type-1 Mamdani system, you can create a:

- Type-1 Sugeno system using a `sugfis` object
- Type-2 Mamdani system using a `mamfisType2` object
- Type-2 Sugeno system using a `sugfisType2` object

For more information on the different types of fuzzy inference systems, see “Mamdani and Sugeno Fuzzy Inference Systems” on page 2-2 and “Type-2 Fuzzy Inference Systems” on page 2-7.

Creation

To create a Mamdani FIS object, use one of the following methods:

- The `mamfis` function.
- If you have input and output training data (`inputData` and `outputData`, respectively), you can use the `genfis` function with the FCM clustering method.

```
opt = genfisOptions('FCMClustering','FISType','mamdani');  
fis = genfis(inputData,outputData,opt);
```

- If you have a `.fis` file for a Mamdani system, you can use the `readfis` function.

Syntax

```
fis = mamfis  
fis = mamfis(Name,Value)
```

Description

`fis = mamfis` creates a Mamdani FIS with default property values. To modify the properties of the fuzzy system, use dot notation.

`fis = mamfis(Name,Value)` specifies FIS configuration information or sets object properties using name-value pair arguments. You can specify multiple name-value pairs. Enclose names in quotes.

Input Arguments

Name-Value Pair Arguments

Specify optional pairs of arguments as `Name1=Value1, ..., NameN=ValueN`, where `Name` is the argument name and `Value` is the corresponding value. Name-value arguments must appear after other arguments, but the order of the pairs does not matter.

Before R2021a, use commas to separate each name and value, and enclose Name in quotes.

Example: `'NumInputs', 2` configures the fuzzy system to have two input variables

NumInputs — Number of FIS inputs

0 (default) | nonnegative integer

Number of FIS inputs, specified as the comma-separated pair consisting of `'NumInputs'` and a nonnegative integer.

NumInputMFs — Number of membership functions for each FIS input

3 (default) | positive integer

Number of membership functions for each FIS input, specified as the comma-separated pair consisting of `'NumInputMFs'` and a positive integer.

NumOutputs — Number of FIS outputs

0 (default) | nonnegative integer

Number of FIS outputs, specified as the comma-separated pair consisting of `'NumOutputs'` and a nonnegative integer.

NumOutputMFs — Number of membership functions for each FIS output

3 (default) | positive integer

Number of membership functions for each FIS output, specified as the comma-separated pair consisting of `'NumOutputMFs'` and a positive integer.

MFType — Membership function type

"trimf" (default) | "gaussmf"

Membership function type for both input and output variables, specified as the comma-separated pair consisting of `"MFType"` and either `"trimf"` (triangular MF) or `"gaussmf"` (Gaussian MF). For each input and output variable, the membership functions are uniformly distributed over the variable range with approximately 80% overlap in the MF supports.

AddRules — Flag for automatically adding rules

"allcombinations" (default) | "none"

Flag for automatically adding rules, specified as the comma-separated pair consisting of `"AddRules"` and one of the following:

- `"allcombinations"` — If both `NumInputs` and `NumOutputs` are greater than zero, create rules with antecedents that contain all input membership function combinations. Each rule consequent contains all the output variables and uses the first membership function of each output.
- `"none"` — Create a FIS without any rules.

Properties

Name — FIS name

"fis" (default) | string | character vector

FIS name, specified as a string or character vector.

AndMethod — AND operator method

"min" (default) | "prod" | string | character vector | function handle

AND operator method for combining fuzzified input values in a fuzzy rule antecedent, specified as one of the following:

- "min" — Minimum of fuzzified input values
- "prod" — Product of fuzzified input values
- String or character vector — Name of a custom AND function in the current working folder or on the MATLAB path
- Function handle — Custom AND function in the current working folder or on the MATLAB path

For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on fuzzy operators and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

OrMethod — OR operator method

"max" (default) | "probor" | string | character vector | function handle

OR operator method for combining fuzzified input values in a fuzzy rule antecedent, specified as one of the following:

- "max" — Maximum of fuzzified input values.
- "probor" — Probabilistic OR of fuzzified input values. For more information, see `probor`.
- String or character vector — Name of a custom OR function in the current working folder or on the MATLAB path.
- Function handle — Custom OR function in the current working folder or on the MATLAB path.

For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on fuzzy operators and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

ImplicationMethod — Implication method

"min" (default) | "prod" | string | character vector | function handle

Implication method for computing the consequent fuzzy set, specified as one of the following:

- "min" — Truncate the consequent membership function at the antecedent result value.
- "prod" — Scale the consequent membership function by the antecedent result value.
- String or character vector — Name of a custom implication function in the current working folder or on the MATLAB path.

- Function handle — Custom implication function in the current working folder or on the MATLAB path.

For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on implication and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

AggregationMethod — Aggregation method

"max" (default) | "sum" | "probor" | string | character vector | function handle

Aggregation method for combining rule consequents, specified as one of the following:

- "max" — Maximum of consequent fuzzy sets
- "sum" — Sum of consequent fuzzy sets
- "probor" — Probabilistic OR of consequent fuzzy sets. For more information, see `probor`.
- String or character vector — Name of a custom aggregation function in the current working folder or on the MATLAB path
- Function handle — Custom aggregation function in the current working folder or on the MATLAB path

For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on aggregation and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

DefuzzificationMethod — Defuzzification method

"centroid" (default) | "bisector" | "mom" | "lom" | "som" | string | character vector | function handle

Defuzzification method for computing crisp output values from the aggregated output fuzzy set, specified as one of the following:

- "centroid" — Centroid of the area under the output fuzzy set
- "bisector" — Bisector of the area under the output fuzzy set
- "mom" — Mean of the values for which the output fuzzy set is maximum
- "lom" — Largest value for which the output fuzzy set is maximum
- "som" — Smallest value for which the output fuzzy set is maximum
- String or character vector — Name of a custom defuzzification function in the current working folder or on the MATLAB path
- Function handle — Custom defuzzification function in the current working folder or on the MATLAB path

For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on defuzzification and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

Inputs — FIS input variablesvector of `fisvar` objects

FIS input variables, specified as a vector of `fisvar` objects. To add and remove input variables, use `addInput` and `removeInput`, respectively.

You can also create a vector of `fisvar` objects and assign it to `Inputs` using dot notation.

You can add membership functions to input variables using the `addMF` function.

Outputs — FIS output variablesvector of `fisvar` objects

FIS output variables, specified as a vector of `fisvar` objects. To add and remove output variables, use `addOutput` and `removeOutput`, respectively.

You can also create a vector of `fisvar` objects and assign it to `Outputs` using dot notation.

You can add membership functions to output variables using the `addMF` function.

Rules — FIS rulesvector of `fisrule` objects

FIS input variables, specified as a vector of `fisrule` objects. To add fuzzy rules, use the `addRule` function.

You can also create a vector of `fisrule` objects and assign it to `Rules` using dot notation.

To remove a rule, set the corresponding rule vector element to `[]`. For example, to remove the tenth rule from the rule list, type:

```
fis.Rules(10) = [];
```

DisableStructuralChecks — Flag for disabling consistency checks`false` (default) | `true`

Flag for disabling consistency checks when property values change, specified as a logical value.

By default, when you change the value of a property of a `mamfis` object, the software verifies whether the new property value is consistent with the other object properties. These checks can affect performance, particularly when creating and updating fuzzy systems within loops.

To disable these checks, which results in faster FIS construction, set `DisableStructuralChecks` to `true`.

Note Disabling structural checks can result in an invalid `mamfis` object.

To reenabling the consistency checks, first verify that the changes you made to the FIS are consistent and produce a valid `mamfis` object. Then, set `DisableStructuralChecks` to `false`. If the `mamfis` object is invalid, reenabling the consistency checks generates an error.

Object Functions

<code>addInput</code>	Add input variable to fuzzy inference system
-----------------------	----------------------------------------------

removeInput	Remove input variable from fuzzy inference system
addOutput	Add output variable to fuzzy inference system
removeOutput	Remove output variable from fuzzy inference system
addRule	Add rule to fuzzy inference system
addMF	Add membership function to fuzzy variable
removeMF	Remove membership function from fuzzy variable
evalfis	Evaluate fuzzy inference system
writeFIS	Save fuzzy inference system to file
convertToType2	Convert type-1 fuzzy inference system into type-2 fuzzy inference system

Examples

Create Mamdani Fuzzy Inference System

Create a Mamdani fuzzy inference system with default property values.

```
fis = mamfis;
```

Modify the system properties using dot notation. For example, configure `fis` to use centroid defuzzification.

```
fis.DefuzzificationMethod = "centroid";
```

Alternatively, you can specify one of more FIS properties when you create a fuzzy system. For example, create a Mamdani fuzzy system with specified AND and OR methods.

```
fis = mamfis("AndMethod", "prod", "OrMethod", "probor");
```

Specify Number of Inputs and Outputs for Mamdani System

Create a Mamdani fuzzy inference system with three inputs and one output.

```
fis = mamfis("NumInputs", 3, "NumOutputs", 1)
```

```
fis =
```

```
  mamfis with properties:
```

```

        Name: "fis"
      AndMethod: "min"
      OrMethod: "max"
  ImplicationMethod: "min"
  AggregationMethod: "max"
DefuzzificationMethod: "centroid"
        Inputs: [1x3 fisvar]
        Outputs: [1x1 fisvar]
          Rules: [1x27 fisrule]
DisableStructuralChecks: 0
```

See 'getTunableSettings' method for parameter optimization.

By default, the software creates a rule for each possible input combination.

Alternative Functionality

App

You can interactively create a Mamdani FIS using the **Fuzzy Logic Designer** app. You can then export the system to the MATLAB workspace.

See Also

`sugfis` | `fisvar` | `fisrule` | `fismf`

Topics

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced in R2018b

mamfistype2

Interval type-2 Mamdani fuzzy inference system

Description

Use a `mamfistype2` object to represent an interval type-2 Mamdani fuzzy inference system (FIS).

As an alternative to a type-2 Mamdani system, you can create a:

- Type-2 Sugeno system using a `sugfistype2` object
- Type-1 Mamdani system using a `mamfis` object
- Type-1 Sugeno system using a `sugfis` object

For more information on the different types of fuzzy inference systems, see “Mamdani and Sugeno Fuzzy Inference Systems” on page 2-2 and “Type-2 Fuzzy Inference Systems” on page 2-7.

Creation

To create a type-2 Mamdani FIS object, use one of the following methods:

- The `mamfistype2` function.
- If you have input and output training data (`inputData` and `outputData`, respectively), you can create a type-1 FIS using the `genfis` function with the FCM clustering method. You can then convert this FIS to a type-2 system using `convertToType2`.

```
opt = genfisOptions('FCMClustering','FISType','mamdani');
fis1 = genfis(inputData,outputData,opt);
fis = convertToType2(fis1);
```

- If you have a `.fis` file for a type-2 Mamdani system, you can use the `readfis` function.

Syntax

```
fis = mamfistype2
fis = mamfistype2(Name,Value)
```

Description

`fis = mamfistype2` creates a type-2 Mamdani FIS with default property values. To modify the properties of the fuzzy system, use dot notation.

`fis = mamfistype2(Name,Value)` specifies FIS configuration information or sets object properties using name-value pair arguments. You can specify multiple name-value pairs. Enclose names in quotes.

Input Arguments

Name-Value Pair Arguments

Specify optional pairs of arguments as `Name1=Value1, ..., NameN=ValueN`, where `Name` is the argument name and `Value` is the corresponding value. Name-value arguments must appear after other arguments, but the order of the pairs does not matter.

Before R2021a, use commas to separate each name and value, and enclose Name in quotes.

Example: `'NumInputs', 2` configures the fuzzy system to have two input variables

NumInputs — Number of FIS inputs

0 (default) | nonnegative integer

Number of FIS inputs, specified as the comma-separated pair consisting of `'NumInputs'` and a nonnegative integer.

NumInputMFs — Number of membership functions for each FIS input

3 (default) | positive integer

Number of membership functions for each FIS input, specified as the comma-separated pair consisting of `'NumInputMFs'` and a positive integer.

NumOutputs — Number of FIS outputs

0 (default) | nonnegative integer

Number of FIS outputs, specified as the comma-separated pair consisting of `'NumOutputs'` and a nonnegative integer.

NumOutputMFs — Number of membership functions for each FIS output

3 (default) | positive integer

Number of membership functions for each FIS output, specified as the comma-separated pair consisting of `'NumOutputMFs'` and a positive integer.

MFType — Membership function type

"trimf" (default) | "gaussmf"

Membership function type for both input and output variables, specified as the comma-separated pair consisting of `"MFType"` and either `"trimf"` (triangular MF) or `"gaussmf"` (Gaussian MF). For each input and output variable, the membership functions are uniformly distributed over the variable range with approximately 80% overlap in the MF supports.

AddRules — Flag for automatically adding rules

"allcombinations" (default) | "none"

Flag for automatically adding rules, specified as the comma-separated pair consisting of `"AddRules"` and one of the following:

- `"allcombinations"` — If both `NumInputs` and `NumOutputs` are greater than zero, create rules with antecedents that contain all input membership function combinations. Each rule consequent contains all the output variables and uses the first membership function of each output.
- `"none"` — Create a FIS without any rules.

Properties

Name — FIS name

"fis" (default) | string | character vector

FIS name, specified as a string or character vector.

AndMethod — AND operator method

"min" (default) | "prod" | string | character vector | function handle

AND operator method for combining fuzzified input values in a fuzzy rule antecedent, specified as one of the following:

- "min" — Minimum of fuzzified input values
- "prod" — Product of fuzzified input values
- String or character vector — Name of a custom AND function in the current working folder or on the MATLAB path
- Function handle — Custom AND function in the current working folder or on the MATLAB path

For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on fuzzy operators and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

OrMethod — OR operator method

"max" (default) | "probor" | string | character vector | function handle

OR operator method for combining fuzzified input values in a fuzzy rule antecedent, specified as one of the following:

- "max" — Maximum of fuzzified input values.
- "probor" — Probabilistic OR of fuzzified input values. For more information, see `probor`.
- String or character vector — Name of a custom OR function in the current working folder or on the MATLAB path.
- Function handle — Custom OR function in the current working folder or on the MATLAB path.

For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on fuzzy operators and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

ImplicationMethod — Implication method

"min" (default) | "prod" | string | character vector | function handle

Implication method for computing the consequent fuzzy set, specified as one of the following:

- "min" — Truncate the consequent membership function at the antecedent result value.
- "prod" — Scale the consequent membership function by the antecedent result value.
- String or character vector — Name of a custom implication function in the current working folder or on the MATLAB path.

- Function handle — Custom implication function in the current working folder or on the MATLAB path.

For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on implication and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

AggregationMethod — Aggregation method

"max" (default) | "sum" | "probor" | string | character vector | function handle

Aggregation method for combining rule consequents, specified as one of the following:

- "max" — Maximum of consequent fuzzy sets
- "sum" — Sum of consequent fuzzy sets
- "probor" — Probabilistic OR of consequent fuzzy sets. For more information, see `probor`.
- String or character vector — Name of a custom aggregation function in the current working folder or on the MATLAB path
- Function handle — Custom aggregation function in the current working folder or on the MATLAB path

For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on aggregation and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

DefuzzificationMethod — Defuzzification method

"centroid" (default)

Defuzzification method for computing crisp output values from the aggregated output fuzzy set. Type-2 Mamdani systems support only centroid defuzzification.

Inputs — FIS input variables

vector of `fisvar` objects

FIS input variables, specified as a vector of `fisvar` objects. To add and remove input variables, use `addInput` and `removeInput`, respectively.

You can also create a vector of `fisvar` objects and assign it to `Inputs` using dot notation.

You can add membership functions to input variables using the `addMF` function.

Outputs — FIS output variables

vector of `fisvar` objects

FIS output variables, specified as a vector of `fisvar` objects. To add and remove output variables, use `addOutput` and `removeOutput`, respectively.

You can also create a vector of `fisvar` objects and assign it to `Outputs` using dot notation.

You can add membership functions to output variables using the `addMF` function.

Rules — FIS rulesvector of `fisrule` objects

FIS input variables, specified as a vector of `fisrule` objects. To add fuzzy rules, use the `addRule` function.

You can also create a vector of `fisrule` objects and assign it to `Rules` using dot notation.

To remove a rule, set the corresponding rule vector element to `[]`. For example, to remove the tenth rule from the rule list, type:

```
fis.Rules(10) = [];
```

DisableStructuralChecks — Flag for disabling consistency checks`false` (default) | `true`

Flag for disabling consistency checks when property values change, specified as a logical value.

By default, when you change the value of a property of a `mamfistype2` object, the software verifies whether the new property value is consistent with the other object properties. These checks can affect performance, particularly when creating and updating fuzzy systems within loops.

To disable these checks, which results in faster FIS construction, set `DisableStructuralChecks` to `true`.

Note Disabling structural checks can result in an invalid `mamfistype2` object.

To reenable the consistency checks, first verify that the changes you made to the FIS are consistent and produce a valid `mamfistype2` object. Then, set `DisableStructuralChecks` to `false`. If the `mamfistype2` object is invalid, reenabling the consistency checks generates an error.

TypeReductionMethod — Type-reduction method`"karnikmendel"` (default) | `"ekm"` | `"iasc"` | `"eiasc"` | string | function handle

Type-reduction method for converting a type-2 output fuzzy set to an interval type-1 fuzzy set, specified as one of the following:

- `"karnikmendel"` — Karnik-Mendel
- `"ekm"` — Enhanced Karnik-Mendel
- `"iasc"` — Iterative algorithm with stop condition
- `"eiasc"` — Enhanced iterative algorithm
- String — Name of a custom type-reduction function in the current working directory or on the MATLAB path.
- Function handle — Function handle to a custom type-reduction function in the current working folder or on the MATLAB path.

For more information on type reduction, see “Type-2 Fuzzy Inference Systems” on page 2-7.

Object Functions

`addInput` Add input variable to fuzzy inference system

removeInput	Remove input variable from fuzzy inference system
addOutput	Add output variable to fuzzy inference system
removeOutput	Remove output variable from fuzzy inference system
addRule	Add rule to fuzzy inference system
addMF	Add membership function to fuzzy variable
removeMF	Remove membership function from fuzzy variable
evalfis	Evaluate fuzzy inference system
writeFIS	Save fuzzy inference system to file
convertToType1	Convert type-2 fuzzy inference system into type-1 fuzzy inference system

Examples

Create Type-2 Mamdani Fuzzy Inference System

Create a type-2 Mamdani fuzzy inference system with default property values.

```
fis = mamfistype2;
```

Modify the system properties using dot notation. For example, set the type reduction method to use the enhanced Karnik-Mendel method.

```
fis.TypeReductionMethod = "ekm";
```

Alternatively, you can specify one of more FIS properties when you create a fuzzy system.

```
fis = mamfistype2('TypeReductionMethod','ekm');
```

Specify Number of Inputs and Outputs for Type-2 Mamdani System

Create a type-2 Mamdani fuzzy inference system with three inputs and one output.

```
fis = mamfis("NumInputs",3,"NumOutputs",1)
```

```
fis =  
    mamfis with properties:
```

```

        Name: "fis"
        AndMethod: "min"
        OrMethod: "max"
        ImplicationMethod: "min"
        AggregationMethod: "max"
        DefuzzificationMethod: "centroid"
        Inputs: [1x3 fisvar]
        Outputs: [1x1 fisvar]
        Rules: [1x27 fisrule]
        DisableStructuralChecks: 0
```

```
See 'getTunableSettings' method for parameter optimization.
```

By default, the software creates a rule for each possible input combination.

See Also

fisvar | fisrule | fismftype2

Topics

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced in R2019b

MembershipFunctionSettings

Tunable parameter settings for fuzzy membership functions

Description

A `MembershipFunctionSettings` object contains tunable parameter settings for a type-1 membership function. Using this object, you can specify the tunability settings for the parameters of the corresponding membership function.

For more information on the tunable settings of a type-2 membership function, see `MembershipFunctionSettingsType2`.

Creation

Create `MembershipFunctionSettings` objects using the `getTunableSettings` function with a `mamfis`, `sugfis`, or `fistree` object. The first and second outputs of `getTunableSettings` contain `VariableSettings` objects for input and output variables, respectively. If a `VariableSettings` object corresponds to a variable with type-1 membership functions, then its `MembershipFunctions` property contains `MembershipFunctionSettings` objects.

Properties

Parameters — Membership function parameter tunable settings

`NumericParameters` object

Membership function parameter tunable settings, specified as a `NumericParameters` object.

Object Functions

`setTunable` Set specified parameter settings as tunable or nontunable

Examples

Obtain Tunable Settings of Input and Output Variables from FIS

Create two fuzzy inference systems, and define the connection between the two.

```

fis1 = mamfis('Name','fis1','NumInputs',2,'NumOutputs',1);
fis2 = sugfis('Name','fis2','NumInputs',2,'NumOutputs',1);
con = ["fis1/output1" "fis2/input1"];

```

Create a tree of fuzzy inference systems.

```
tree = fistree([fis1 fis2],con);
```

Obtain the tunable settings of input and output variables of the fuzzy inference system.

```
[in,out] = getTunableSettings(tree)
```

```
in=4x1 object
  4x1 VariableSettings array with properties:

    Type
    VariableName
    MembershipFunctions
    FISName
```

```
out=2x1 object
  2x1 VariableSettings array with properties:

    Type
    VariableName
    MembershipFunctions
    FISName
```

You can use dot notation to specify the tunable settings of input and output variables.

For the first membership function of input 1, set the first and third parameters to tunable.

```
in(1).MembershipFunctions(1).Parameters.Free = [1 0 1];
```

For the first membership function of input 2, set the minimum parameter range to 0.

```
in(2).MembershipFunctions(1).Parameters.Minimum = 0;
```

For the first membership function of output 2, set the maximum parameter range to 1.

```
out(2).MembershipFunctions(1).Parameters.Maximum = 1;
```

See Also

[getTunableSettings](#) | [VariableSettings](#) | [NumericParameters](#)

Introduced in R2019a

MembershipFunctionSettingsType2

Tunable parameter settings for type-2 fuzzy membership functions

Description

A `MembershipFunctionSettingsType2` object contains tunable parameter settings for a type-2 membership function. Using this object, you can specify the tunability settings for the corresponding MF, including the upper MF parameters, the lower MF scale, and the lower MF lag.

For more information on the tunable settings of a type-1 membership function, see `MembershipFunctionSettings`.

Creation

Create `MembershipFunctionSettingsType2` objects using the `getTunableSettings` function with a `mamfistype2`, `sugfistype2`, or `fistree` object. The first and second outputs of `getTunableSettings` contain `VariableSettings` objects for input and output variables, respectively. If a `VariableSettings` object corresponds to a variable with type-2 membership functions, then its `MembershipFunctions` property contains `MembershipFunctionSettingsType2` objects.

Properties

UpperParameters — Upper membership function parameter tunable settings

`NumericParameters` object

Upper membership function parameter tunable settings, specified as a `NumericParameters` object.

LowerScale — Lower membership function scale tunable settings

`NumericParameters` object

Lower membership function scale tunable settings, specified as a `NumericParameters` object.

LowerLag — Lower membership function lag tunable settings

`NumericParameters` object

Lower membership function lag tunable settings, specified as a `NumericParameters` object.

Object Functions

`setTunable` Set specified parameter settings as tunable or nontunable

Examples

Obtain Tunable Settings of Input and Output Variables from Type-2 FIS

Create a type-2 fuzzy inference system.


```
fis = mamfistype2('Name','fis1','NumInputs',2,'NumOutputs',1);
```

Obtain the tunable settings of the input and output variables of the fuzzy inference system.

```
[in,out] = getTunableSettings(fis);
```

You can use dot notation to specify the tunable settings of the membership functions of the input and output variables.

For the first membership function of input 1, set the first and third upper membership function parameters as tunable.

```
in(1).MembershipFunctions(1).UpperParameters.Free = [1 0 1];
```

For the first membership function of input 2, set the tunable range of the lower membership function scale to be between 0.7 and 0.9.

```
in(2).MembershipFunctions(1).LowerScale.Minimum = 0.7;  
in(2).MembershipFunctions(1).LowerScale.Maximum = 0.9;
```

For the first membership function of output 1, set the tunable range of the lower membership function lag to be between 0.1 and 0.4.

```
in(2).MembershipFunctions(1).LowerLag.Minimum = 0.1;  
in(2).MembershipFunctions(1).LowerLag.Maximum = 0.4;
```

See Also

[getTunableSettings](#) | [VariableSettings](#) | [NumericParameters](#) | [MembershipFunctionSettings](#)

Introduced in R2019b

NumericParameters

Tunable numeric parameter settings of membership functions

Description

A `NumericParameters` object contains tunable settings for the numeric properties of a fuzzy membership function.

Creation

Create a `NumericParameters` object using the `getTunableSettings` function. The first and second outputs of `getTunableSettings` contain `VariableSettings` objects for input and output variables, respectively. The `MembershipFunctions` property of each `VariableSettings` object contains `NumericParameters` objects for specifying the tunable settings of the membership function properties.

Properties

Free — Parameter values available for tuning

vector of logical values | 1 | 0

Parameter values available for tuning, specified as one of the following:

- Vector of logical values when the `NumericParameters` contains tunable settings for the `Parameters` property of a type-1 membership function or the `UpperParameters` property of a type-2 membership function
- Logical 1 or 0 when the `NumericParameters` object contains tunable settings for either the `LowerScale` or `LowerLag` properties of a type-2 membership function

Minimum — Minimum parameter values

vector | scalar

Minimum parameter values, specified as one of the following:

- Vector when the `NumericParameters` contains tunable settings for the `Parameters` property of a type-1 membership function or the `UpperParameters` property of a type-2 membership function
- Scalar value when the `NumericParameters` object contains tunable settings for either the `LowerScale` or `LowerLag` properties of a type-2 membership function

Maximum — Maximum parameter values

vector | scalar

Maximum parameter values, specified as one of the following:

- Vector when the `NumericParameters` contains tunable settings for the `Parameters` property of a type-1 membership function or the `UpperParameters` property of a type-2 membership function

- Scalar value when the NumericParameters object contains tunable settings for either the LowerScale or LowerLag properties of a type-2 membership function.

Examples

Obtain Tunable Settings of Input and Output Variables from FIS

Create two fuzzy inference systems, and define the connection between the two.

```

fis1 = mamfis('Name','fis1','NumInputs',2,'NumOutputs',1);
fis2 = sugfis('Name','fis2','NumInputs',2,'NumOutputs',1);
con = ["fis1/output1" "fis2/input1"];

```

Create a tree of fuzzy inference systems.

```
tree = fistree([fis1 fis2],con);
```

Obtain the tunable settings of input and output variables of the fuzzy inference system.

```
[in,out] = getTunableSettings(tree)
```

```

in=4x1 object
  4x1 VariableSettings array with properties:

```

```

    Type
    VariableName
    MembershipFunctions
    FISName

```

```

out=2x1 object
  2x1 VariableSettings array with properties:

```

```

    Type
    VariableName
    MembershipFunctions
    FISName

```

You can use dot notation to specify the tunable settings of input and output variables.

For the first membership function of input 1, set the first and third parameters to tunable.

```
in(1).MembershipFunctions(1).Parameters.Free = [1 0 1];
```

For the first membership function of input 2, set the minimum parameter range to 0.

```
in(2).MembershipFunctions(1).Parameters.Minimum = 0;
```

For the first membership function of output 2, set the maximum parameter range to 1.

```
out(2).MembershipFunctions(1).Parameters.Maximum = 1;
```

Obtain Tunable Settings of Input and Output Variables from Type-2 FIS

Create a type-2 fuzzy inference system.

```
fis = mamfistype2('Name','fis1','NumInputs',2,'NumOutputs',1);
```

Obtain the tunable settings of the input and output variables of the fuzzy inference system.

```
[in,out] = getTunableSettings(fis);
```

You can use dot notation to specify the tunable settings of the membership functions of the input and output variables.

For the first membership function of input 1, set the first and third upper membership function parameters as tunable.

```
in(1).MembershipFunctions(1).UpperParameters.Free = [1 0 1];
```

For the first membership function of input 2, set the tunable range of the lower membership function scale to be between 0.7 and 0.9.

```
in(2).MembershipFunctions(1).LowerScale.Minimum = 0.7;  
in(2).MembershipFunctions(1).LowerScale.Maximum = 0.9;
```

For the first membership function of output 1, set the tunable range of the lower membership function lag to be between 0.1 and 0.4.

```
in(2).MembershipFunctions(1).LowerLag.Minimum = 0.1;  
in(2).MembershipFunctions(1).LowerLag.Maximum = 0.4;
```

See Also

[getTunableSettings](#) | [VariableSettings](#) | [MembershipFunctionSettings](#)

Introduced in R2019a

RuleSettings

Tunable parameter settings of fuzzy rules

Description

A RuleSettings object is created using the `getTunableSettings` function with a `mamfis`, `sugfis`, or `fistree` object. When the third output is specified, `getTunableSettings` returns tunable parameter settings of fuzzy rules. Specify the settings of the Antecedent and Consequent properties.

Creation

Create a RuleSettings object using `getTunableSettings` with three outputs.

Properties

FISName — Name of fuzzy inference system

string

This property is read-only.

Name of fuzzy inference system, specified as a string.

Index — Index of rule in fuzzy inference system

double

This property is read-only.

Index of rule in fuzzy inference system, specified as an integer.

Antecedent — Antecedent parameter settings of rule

ClauseParameters object

Antecedent parameter settings of rule, specified as a ClauseParameters object. Each antecedent parameter consists of the properties `AllowNot`, `AllowEmpty`, and `Free`. You can specify these properties.

Consequent — Consequent parameter settings of rule

ClauseParameters object

Consequent parameter settings of rule, specified as a ClauseParameters object. Each consequent parameter consists of the properties `AllowNot`, `AllowEmpty`, and `Free`. You can specify these properties.

Object Functions

`setTunable` Set specified parameter settings as tunable or nontunable

Examples

Obtain Tunable Settings of Rules from FIS

Create two fuzzy inference systems, and define the connection between the two.

```
fis1 = mamfis('Name','fis1','NumInputs',2,'NumOutputs',1);
fis2 = sugfis('Name','fis2','NumInputs',2,'NumOutputs',1);
con = ["fis1/output1" "fis2/input1"];
```

Create a tree of fuzzy inference systems.

```
tree = fistree([fis1 fis2],con);
```

Obtain the tunable settings of rules of the fuzzy inference system.

```
[~,~,rule] = getTunableSettings(tree)
```

```
rule=18x1 object
  16x1 RuleSettings array with properties:
```

```
    Index
  Antecedent
  Consequent
  FISName
      :
```

You can use dot notation to specify the tunable settings of rules.

For the first rule, do not tune input 1 membership function index and do not ignore output 1 membership function index.

```
rule(1).Antecedent.Free(1) = false;
rule(1).Consequent.AllowEmpty(1) = false;
```

For the second rule, allow NOT logic for input 2 membership function index.

```
rule(2).Antecedent.AllowNot(2) = true;
```

See Also

[getTunableSettings](#) | [ClauseParameters](#) | [VariableSettings](#)

Introduced in R2019a

sugfis

Sugeno fuzzy inference system

Description

Use a `sugfis` object to represent a type-1 Sugeno fuzzy inference system (FIS).

As an alternative to a type-1 Sugeno system, you can create a:

- Type-1 Mamdani system using a `mamfis` object
- Type-2 Sugeno system using a `sugfistype2` object
- Type-2 Mamdani system using a `mamfistype2` object

For more information on the different types of fuzzy inference systems, see “Mamdani and Sugeno Fuzzy Inference Systems” on page 2-2 and “Type-2 Fuzzy Inference Systems” on page 2-7.

Creation

To create a Sugeno FIS object, use one of the following methods:

- The `sugfis` function.
- If you have input/output data, you can use the `genfis` function.
- If you have a `.fis` file for a Sugeno system, you can use the `readfis` function.
- Convert an existing Mamdani FIS to a Sugeno FIS using `convertToSugeno`.

Syntax

```
fis = sugfis
fis = sugfis(Name,Value)
```

Description

`fis = sugfis` creates a Sugeno FIS with default property values. To modify the properties of the fuzzy system, use dot notation.

`fis = sugfis(Name,Value)` specifies FIS configuration information or sets object properties using name-value pair arguments. You can specify multiple name-value pairs. Enclose names in quotes.

Input Arguments

Name-Value Pair Arguments

Specify optional pairs of arguments as `Name1=Value1, . . . , NameN=ValueN`, where `Name` is the argument name and `Value` is the corresponding value. Name-value arguments must appear after other arguments, but the order of the pairs does not matter.

Before R2021a, use commas to separate each name and value, and enclose Name in quotes.

Example: 'NumInputs', 2 configures the fuzzy system to have two input variables

NumInputs — Number of FIS inputs

0 (default) | nonnegative integer

Number of FIS inputs, specified as the comma-separated pair consisting of 'NumInputs' and a nonnegative integer.

NumInputMFs — Number of membership functions for each FIS input

3 (default) | positive integer

Number of membership functions for each FIS input, specified as the comma-separated pair consisting of 'NumInputMFs' and a positive integer.

NumOutputs — Number of FIS outputs

0 (default) | nonnegative integer

Number of FIS outputs, specified as the comma-separated pair consisting of 'NumOutputs' and a nonnegative integer.

NumOutputMFs — Number of membership functions for each FIS output

3 (default) | positive integer

Number of membership functions for each FIS output, specified as the comma-separated pair consisting of 'NumOutputMFs' and a positive integer.

MFType — Membership function type

"trimf" (default) | "gaussmf"

Membership function type for input variables, specified as the comma-separated pair consisting of 'MFType' and either "trimf" (triangular MF) or "gaussmf" (Gaussian MF). For each input variable, the membership functions are uniformly distributed over the variable range with approximately 80% overlap in the MF supports.

Output membership functions are set to "constant" and uniformly distributed over the output variable ranges.

AddRules — Flag for automatically adding rules

"allcombinations" (default) | "none"

Flag for automatically adding rules, specified as the comma-separated pair consisting of "AddRules" and one of the following:

- "allcombinations" — If both NumInputs and NumOutputs are greater than zero, create rules with antecedents that contain all input membership function combinations. Each rule consequent contains all the output variables and uses the first membership function of each output.
- "none" — Create a FIS without any rules.

Properties**Name — FIS name**

"fis" (default) | string | character vector

FIS name, specified as a string or character vector.

AndMethod — AND operator method

"prod" (default) | "min" | string | character vector | function handle

AND operator method for combining fuzzified input values in a fuzzy rule antecedent, specified as one of the following:

- "prod" — Product of fuzzified input values
- "min" — Minimum of fuzzified input values
- String or character vector — Name of a custom AND function in the current working folder or on the MATLAB path
- Function handle — Custom AND function in the current working folder or on the MATLAB path

For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on fuzzy operators and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

OrMethod — OR operator method

"probor" (default) | "max" | string | character vector | function handle

OR operator method for combining fuzzified input values in a fuzzy rule antecedent, specified as one of the following:

- "probor" — Probabilistic OR of fuzzified input values. For more information, see `probor`.
- "max" — Maximum of fuzzified input values.
- String or character vector — Name of a custom OR function in the current working folder or on the MATLAB path.
- Function handle — Custom OR function in the current working folder or on the MATLAB path.

For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on fuzzy operators and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

ImplicationMethod — Implication method

"prod" (default)

Implication method for computing consequent fuzzy set, specified as "prod". Sugeno systems always use the "prod" implication method, which scales the consequent membership function by the antecedent result value.

For more information on implication and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

AggregationMethod — Aggregation method

"sum" (default)

Aggregation method for combining rule consequents, specified as "sum". Sugeno systems always use the "sum" aggregation method, which is the sum of the consequent fuzzy sets.

For more information on aggregation and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

DefuzzificationMethod — Defuzzification method

"wtaver" (default) | "wtsum"

Defuzzification method for computing crisp output values from the aggregated output fuzzy set, specified as one of the following:

- "wtaver" — Weighted average of all rule outputs
- "wtsum" — Weighted sum of all rule outputs

For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on defuzzification and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

Inputs — FIS input variables

vector of `fisvar` objects

FIS input variables, specified as a vector of `fisvar` objects. To add and remove input variables, use `addInput` and `removeInput`, respectively. You can modify the properties of the input variables using dot notation.

You can also create a vector of `fisvar` objects and assign it to `Inputs` using dot notation.

You can add membership functions to input variables using the `addMF` function.

Outputs — FIS output variables

vector of `fisvar` objects

FIS output variables, specified as a vector of `fisvar` objects. To add and remove output variables, use `addOutput` and `removeOutput`, respectively.

You can also create a vector of `fisvar` objects and assign it to `Outputs` using dot notation.

You can add membership functions to output variables using the `addMF` function.

Rules — FIS rules

vector of `fisrule` objects

FIS input variables, specified as a vector of `fisrule` objects. To add fuzzy rules, use the `addRule` function.

You can also create a vector of `fisrule` objects and assign it to `Rules` using dot notation.

To remove a rule, set the corresponding rule vector element to `[]`. For example, to remove the tenth rule from the rule list, type:

```
fis.Rules(10) = [];
```

DisableStructuralChecks — Flag for disabling consistency checks

false (default) | true

Flag for disabling consistency checks when property values change, specified as a logical value.

By default, when you change the value of a property of a `sugfis` object, the software verifies whether the new property value is consistent with the other object properties. These checks can affect performance, particularly when creating and updating fuzzy systems within loops.

To disable these checks, which results in faster FIS construction, set `DisableStructuralChecks` to `true`.

Note Disabling structural checks can result in an invalid `sugfis` object.

To reenable the consistency checks, first verify that the changes you made to the FIS are consistent and produce a valid `sugfis` object. Then, set `DisableStructuralChecks` to `false`. If the `sugfis` object is invalid, reenabling the consistency checks generates an error.

Object Functions

<code>addInput</code>	Add input variable to fuzzy inference system
<code>removeInput</code>	Remove input variable from fuzzy inference system
<code>addOutput</code>	Add output variable to fuzzy inference system
<code>removeOutput</code>	Remove output variable from fuzzy inference system
<code>addRule</code>	Add rule to fuzzy inference system
<code>addMF</code>	Add membership function to fuzzy variable
<code>removeMF</code>	Remove membership function from fuzzy variable
<code>evalfis</code>	Evaluate fuzzy inference system
<code>writeFIS</code>	Save fuzzy inference system to file
<code>convertToType2</code>	Convert type-1 fuzzy inference system into type-2 fuzzy inference system

Examples

Create Sugeno Fuzzy Inference System

Create a Sugeno fuzzy inference system with default property values.

```
fis = sugfis;
```

Modify the system properties using dot notation. For example, configure `fis` to use weighted-sum defuzzification.

```
fis.DefuzzificationMethod = "wtsum";
```

Alternatively, you can specify one or more FIS properties when you create a fuzzy system. For example, create a Sugeno fuzzy system with specified AND and OR methods.

```
fis = sugfis("AndMethod", "min", "OrMethod", "max");
```

Specify Number of Inputs and Outputs for Sugeno System

Create a Sugeno fuzzy inference system with three inputs and one output.

```
fis = sugfis("NumInputs", 3, "NumOutputs", 1)
```

```
fis =
  sugfis with properties:

        Name: "fis"
      AndMethod: "prod"
      OrMethod: "probor"
    ImplicationMethod: "prod"
    AggregationMethod: "sum"
  DefuzzificationMethod: "wtaver"
        Inputs: [1x3 fisvar]
        Outputs: [1x1 fisvar]
        Rules: [1x27 fisrule]
  DisableStructuralChecks: 0

  See 'getTunableSettings' method for parameter optimization.
```

By default, the software creates a rule for each possible input combination.

Create Sugeno FIS with Linear Output Membership Functions

Load a Sugeno FIS from a file.

```
fis = readfis('sugeno1');
```

The output variable has two membership functions. View the properties of the first membership function.

```
fis.Outputs(1).MembershipFunctions(1)
```

```
ans =
  fismf with properties:

        Type: "linear"
    Parameters: [-1 -1]
        Name: "line1"
```

View the properties of the second membership function.

```
fis.Outputs(1).MembershipFunctions(2)
```

```
ans =
  fismf with properties:

        Type: "linear"
    Parameters: [1 -1]
        Name: "line2"
```

The input membership functions and rules define which of these output functions are expressed and when.

```
fis.Rules
```

```
ans =
  1x2 fisrule array with properties:
```

Description
 Antecedent
 Consequent
 Weight
 Connection


Details:

Description

```
1 "input==low => output=line1 (1)"
2 "input==high => output=line2 (1)"
```


Plot the input membership functions of this system. The `low` membership function generally refers to input values less than zero, while `high` refers to values greater than zero.

```
plotmf(fis, 'input', 1)
```



Plot the output surface for this FIS.

```
gensurf(fis)
```



The overall fuzzy system output switches smoothly from the line called `line1` to the line called `line2`.

Alternative Functionality

App

You can interactively create a Sugeno FIS using the **Fuzzy Logic Designer** or **Neuro-Fuzzy Designer** apps. You can then export the system to the MATLAB workspace.

See Also

`mamfis` | `fisvar` | `fisrule` | `fismf`

Topics

“Build Fuzzy Systems at the Command Line” on page 2-31

Introduced in R2018b

sugfistype2

Interval type-2 Sugeno fuzzy inference system

Description

Use a `sugfistype2` object to represent an interval type-2 Sugeno fuzzy inference system (FIS).

As an alternative to a type-2 Sugeno system, you can create a:

- Type-2 Mamdani system using a `mamfistype2` object
- Type-1 Sugeno system using a `sugfis` object
- Type-1 Mamdani system using a `mamfis` object

For more information on the different types of fuzzy inference systems, see “Mamdani and Sugeno Fuzzy Inference Systems” on page 2-2 and “Type-2 Fuzzy Inference Systems” on page 2-7.

Creation

To create a type-2 Sugeno FIS object, use one of the following methods:

- The `sugfistype2` function.
- If you have input/output data, you can use the `genfis` function. You can then convert this FIS to a type-2 system using `convertToType2`.
- If you have a `.fis` file for a Sugeno system, you can use the `readfis` function.
- Convert an existing type-2 Mamdani FIS to a Sugeno FIS using `convertToSugeno`.

Syntax

```
fis = sugfistype2
fis = sugfistype2(Name,Value)
```

Description

`fis = sugfistype2` creates a type-2 Sugeno FIS with default property values. To modify the properties of the fuzzy system, use dot notation.

`fis = sugfistype2(Name,Value)` specifies FIS configuration information or sets object properties using name-value pair arguments. You can specify multiple name-value pairs. Enclose names in quotes.

Input Arguments

Name-Value Pair Arguments

Specify optional pairs of arguments as `Name1=Value1, ..., NameN=ValueN`, where `Name` is the argument name and `Value` is the corresponding value. Name-value arguments must appear after other arguments, but the order of the pairs does not matter.

Before R2021a, use commas to separate each name and value, and enclose Name in quotes.

Example: 'NumInputs', 2 configures the fuzzy system to have two input variables

NumInputs — Number of FIS inputs

0 (default) | nonnegative integer

Number of FIS inputs, specified as the comma-separated pair consisting of 'NumInputs' and a nonnegative integer.

NumInputMFs — Number of membership functions for each FIS input

3 (default) | positive integer

Number of membership functions for each FIS input, specified as the comma-separated pair consisting of 'NumInputMFs' and a positive integer.

NumOutputs — Number of FIS outputs

0 (default) | nonnegative integer

Number of FIS outputs, specified as the comma-separated pair consisting of 'NumOutputs' and a nonnegative integer.

NumOutputMFs — Number of membership functions for each FIS output

3 (default) | positive integer

Number of membership functions for each FIS output, specified as the comma-separated pair consisting of 'NumOutputMFs' and a positive integer.

MFType — Membership function type

"trimf" (default) | "gaussmf"

Membership function type for input variables, specified as the comma-separated pair consisting of 'MFType' and either "trimf" (triangular MF) or "gaussmf" (Gaussian MF). For each input variable, the membership functions are uniformly distributed over the variable range with approximately 80% overlap in the MF supports.

Output membership functions are set to "constant" and uniformly distributed over the output variable ranges.

AddRules — Flag for automatically adding rules

"allcombinations" (default) | "none"

Flag for automatically adding rules, specified as the comma-separated pair consisting of "AddRules" and one of the following:

- "allcombinations" — If both NumInputs and NumOutputs are greater than zero, create rules with antecedents that contain all input membership function combinations. Each rule consequent contains all the output variables and uses the first membership function of each output.
- "none" — Create a FIS without any rules.

Properties

Name — FIS name

"fis" (default) | string | character vector

FIS name, specified as a string or character vector.

AndMethod — AND operator method

"prod" (default) | "min" | string | character vector | function handle

AND operator method for combining fuzzified input values in a fuzzy rule antecedent, specified as one of the following:

- "prod" — Product of fuzzified input values
- "min" — Minimum of fuzzified input values
- String or character vector — Name of a custom AND function in the current working folder or on the MATLAB path
- Function handle — Custom AND function in the current working folder or on the MATLAB path

For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on fuzzy operators and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

OrMethod — OR operator method

"probor" (default) | "max" | string | character vector | function handle

OR operator method for combining fuzzified input values in a fuzzy rule antecedent, specified as one of the following:

- "probor" — Probabilistic OR of fuzzified input values. For more information, see `probor`.
- "max" — Maximum of fuzzified input values.
- String or character vector — Name of a custom OR function in the current working folder or on the MATLAB path.
- Function handle — Custom OR function in the current working folder or on the MATLAB path.

For more information on using custom functions, see “Build Fuzzy Systems Using Custom Functions” on page 2-40.

For more information on fuzzy operators and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

ImplicationMethod — Implication method

"prod" (default)

Implication method for computing consequent fuzzy set, specified as "prod". Sugeno systems always use the "prod" implication method, which scales the consequent membership function by the antecedent result value.

For more information on implication and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

AggregationMethod — Aggregation method

"sum" (default)

Aggregation method for combining rule consequents, specified as "sum". Sugeno systems always use the "sum" aggregation method, which is the sum of the consequent fuzzy sets.

For more information on aggregation and the fuzzy inference process, see “Fuzzy Inference Process” on page 1-19.

DefuzzificationMethod — Defuzzification method

"wtaver" (default)

Defuzzification method for computing crisp output values from the aggregated output fuzzy set. Type-2 Sugeno systems support only weighted-average defuzzification.

Inputs — FIS input variables

vector of `fisvar` objects

FIS input variables, specified as a vector of `fisvar` objects. To add and remove input variables, use `addInput` and `removeInput`, respectively. You can modify the properties of the input variables using dot notation.

You can also create a vector of `fisvar` objects and assign it to `Inputs` using dot notation.

You can add membership functions to input variables using the `addMF` function.

Outputs — FIS output variables

vector of `fisvar` objects

FIS output variables, specified as a vector of `fisvar` objects. To add and remove output variables, use `addOutput` and `removeOutput`, respectively.

You can also create a vector of `fisvar` objects and assign it to `Outputs` using dot notation.

You can add membership functions to output variables using the `addMF` function.

Rules — FIS rules

vector of `fisrule` objects

FIS input variables, specified as a vector of `fisrule` objects. To add fuzzy rules, use the `addRule` function.

You can also create a vector of `fisrule` objects and assign it to `Rules` using dot notation.

To remove a rule, set the corresponding rule vector element to `[]`. For example, to remove the tenth rule from the rule list, type:

```
fis.Rules(10) = [];
```

DisableStructuralChecks — Flag for disabling consistency checks

false (default) | true

Flag for disabling consistency checks when property values change, specified as a logical value.

By default, when you change the value of a property of a `sugfistype2` object, the software verifies whether the new property value is consistent with the other object properties. These checks can affect performance, particularly when creating and updating fuzzy systems within loops.

To disable these checks, which results in faster FIS construction, set `DisableStructuralChecks` to `true`.

Note Disabling structural checks can result in an invalid `sugfistype2` object.

To reenable the consistency checks, first verify that the changes you made to the FIS are consistent and produce a valid `sugfistype2` object. Then, set `DisableStructuralChecks` to `false`. If the `sugfistype2` object is invalid, reenabling the consistency checks generates an error.

TypeReductionMethod — Type-reduction method

"karnikmendel" (default) | "ekm" | "iasc" | "eiasc" | string | function handle

Type-reduction method for converting a type-2 output fuzzy set to an interval type-1 fuzzy set, specified as one of the following:

- "karnikmendel" — Karnik-Mendel
- "ekm" — Enhanced Karnik-Mendel
- "iasc" — Iterative algorithm with stop condition
- "eiasc" — Enhanced iterative algorithm
- String — Name of a custom type-reduction function in the current working directory or on the MATLAB path.
- Function handle — Function handle to a custom type-reduction function in the current working folder or on the MATLAB path.

For more information on type reduction, see "Type-2 Fuzzy Inference Systems" on page 2-7.

Object Functions

<code>addInput</code>	Add input variable to fuzzy inference system
<code>removeInput</code>	Remove input variable from fuzzy inference system
<code>addOutput</code>	Add output variable to fuzzy inference system
<code>removeOutput</code>	Remove output variable from fuzzy inference system
<code>addRule</code>	Add rule to fuzzy inference system
<code>addMF</code>	Add membership function to fuzzy variable
<code>removeMF</code>	Remove membership function from fuzzy variable
<code>evalfis</code>	Evaluate fuzzy inference system
<code>writeFIS</code>	Save fuzzy inference system to file
<code>convertToType1</code>	Convert type-2 fuzzy inference system into type-1 fuzzy inference system

Examples

Create Type-2 Sugeno Fuzzy Inference System

Create a type-2 Sugeno fuzzy inference system with default property values.

```
fis = sugfistype2;
```

Modify the system properties using dot notation. For example, set the type reduction method to use the enhanced Karnik-Mendel method.

```
fis.TypeReductionMethod = "ekm";
```

Alternatively, you can specify one or more FIS properties when you create a fuzzy system.

```
fis = sugfistype2('TypeReductionMethod','ekm');
```

Specify Number of Inputs and Outputs for Type-2 Sugeno System

Create a type-2 Sugeno fuzzy inference system with three inputs and one output. A type-2 Sugeno system uses type-2 membership functions only for its input variables.

```
fis = sugfistype2("NumInputs",3,"NumOutputs",1)
```

```
fis =  
    sugfistype2 with properties:  
  
        Name: "fis"  
        AndMethod: "prod"  
        OrMethod: "probor"  
        ImplicationMethod: "prod"  
        AggregationMethod: "sum"  
        DefuzzificationMethod: "wtaver"  
        Inputs: [1x3 fisvar]  
        Outputs: [1x1 fisvar]  
        Rules: [1x27 fisrule]  
        DisableStructuralChecks: 0  
        TypeReductionMethod: "karnikmendel"
```

See 'getTunableSettings' method for parameter optimization.

By default, the software creates a rule for each possible input combination.

See Also

[fisvar](#) | [fisrule](#) | [fismftype2](#)

Topics

"Build Fuzzy Systems at the Command Line" on page 2-31

Introduced in R2019b

tunefisOptions

Option set for `tunefis` function

Description

Use a `tunefisOptions` object to specify options for tuning fuzzy systems using the `tunefis` function. You can specify options such as the optimization method, optimization type, and distance metric for optimization cost calculation.

Creation

Syntax

```
opt = tunefisOptions  
opt = tunefisOptions(Name,Value)
```

Description

`opt = tunefisOptions` creates a default option set for tuning a fuzzy inference system using the `tunefis` function. To modify the properties of this option set for your specific application, use dot notation.

`opt = tunefisOptions(Name,Value)` creates an option set with “Properties” on page 9-85 specified using one or more name-value pair arguments.

Properties

Method — Tuning algorithm

"ga" (default) | "particleswarm" | "patternsearch" | "simulannealbnd" | "anfis"

Tuning algorithm, specified as one of the following:

- "ga" — genetic algorithm
- "particleswarm" — particle swarm
- "patternsearch" — pattern search
- "simulannealbnd" — simulated annealing algorithm
- "anfis" — adaptive neuro-fuzzy

These tuning algorithms use solvers from the Global Optimization Toolbox software, except for "anfis". The `MethodOptions` property differs for each algorithm, and corresponds to the options input argument for the respective solver. If you specify `MethodOptions` without specifying `Method`, then the tuning method is determined based on `MethodOptions`.

The "anfis" tuning method supports tuning only type-1 Sugeno fuzzy inference systems with one output variable.

MethodOptions — Tuning algorithm options

options created using `optimoptions`

Tuning algorithm options, specified as an option object for the tuning algorithm specified by `Method`. This property differs for each algorithm and is created using `optimoptions`. If you do not specify `MethodOptions`, `tunefis` creates a default option object for the tuning method specified in `Method`. To modify the options in `MethodOptions`, use dot notation.

OptimizationType — Type of optimization

"tuning" (default) | "learning"

Type of optimization, specified as one of the following:

- "tuning" — Optimize the existing input, output, and rule parameters without learning new rules.
- "learning" — Learn new rules up to the maximum number of rules specified by `NumMaxRules`.

The "anfis" algorithm supports only "tuning" optimization.

NumMaxRules — Maximum number of rules in a FIS

Inf (default) | integer

Maximum number of rules in a FIS after optimization, specified as an integer. The number of rules in a FIS (after optimization) can be less than `NumMaxRules`, since duplicate rules with the same antecedent values are removed from the rule base.

When `NumMaxRules` is `Inf`, `tunefis` sets `NumMaxRules` to the maximum number of possible rules for the FIS. This maximum value is computed based on the number of input variables and the number of membership functions for each input variable.

When tuning the parameters of a `fistree` object, `NumMaxRules` indicates the maximum number of rules for each FIS in the `fistree`.

The "anfis" tuning method ignores this option.

IgnoreInvalidParameters — Flag for ignoring invalid parameters

true (default) | false

Flag for ignoring invalid parameters, specified as either `true` or `false`. When `IgnoreInvalidParameters` is `true`, the `tunefis` function ignores invalid parameter values generated during the tuning process.

The "anfis" tuning method ignores this option.

DistanceMetric — Type of distance metric

"rmse" (default) | "norm1" | "norm2"

Type of distance metric used for computing the cost for the optimized parameter values with respect to the training data, specified as one of the following:

- "rmse" — Root-mean-squared error
- "norm1" — Vector 1-norm
- "norm2" — Vector 2-norm

For more information on vector norms, see `norm`.

The "anfis" tuning method supports only the "rmse" metric.

UseParallel – Flag for using parallel computing

false (default) | true

Flag for using parallel computing, specified as either true or false. When UseParallel is true, the tunefis function uses parallel computation in the optimization process. Using parallel computing requires Parallel Computing Toolbox™ software.

The "anfis" tuning method does not support parallel computation.


KFoldValue – Number of cross validations to perform

0 (default) | nonnegative integer

Number of cross validations to perform, specified as a nonnegative integer less than or equal to the number of rows in the training data.

When KFoldValue is 0 or 1, tunefis uses the entire input data set for training and does not perform validation.

Otherwise, tunefis randomly partitions the input data into KFoldValue subsets of approximately equal size. The function then performs KFoldValue training-validation iterations. For each iteration, one data subset is used as validation data with the remaining subsets used as training data. The following figure shows the data partition and iterations for KFoldValue = 4.



For an example that tunes a fuzzy inference system using k-fold cross validation, see "Optimize FIS Parameters with k-Fold Cross-Validation" on page 3-51.

The "anfis" tuning method ignores this option.

ValidationTolerance – Maximum allowable increase in validation cost

0.1 (default) | value in the range [0,1]

Maximum allowable increase in validation cost when using k-fold cross validation, specified as a scalar value in the range [0,1]. A higher `ValidationTolerance` value produces a longer training-validation iteration, with an increased possibility of data overfitting.

The increase in validation cost, ΔC , is the difference between the average validation cost and the minimum validation cost, C_{min} , for the current training-validation iteration. The average validation cost is a moving average with a window size equal to `ValidationWindowSize`.

`tunefis` stops the current training-validation iteration when the ratio between ΔC and C_{min} exceeds `ValidationTolerance`.

`ValidationTolerance` is ignored when `KFoldValue` is 0 or 1.

The "anfis" tuning method ignores this option.

ValidationWindowSize — Window size for computing average validation cost

5 (default) | positive integer

Window size for computing average validation cost, specified as a positive integer. The validation cost moving average is computed over the last N validation cost values, where N is equal to `ValidationWindowSize`. A higher `ValidationWindowSize` value produces a longer training-validation iteration, with an increased possibility of data overfitting. A lower window size can cause early termination of the tuning process when the training data is noisy.

`ValidationWindowSize` is ignored when `KFoldValue` is 0 or 1.

The "anfis" tuning method ignores this option.

Display — Data to display in command window during training

"all" (default) | "tuningonly" | "validationonly" | "none"

Data to display in command window during training, specified as one of the following values.

- "all" — Display both training and validation results.
- "tuningonly" — Display only training results.
- "validationonly" — Display only validation results.
- "none" — Display neither training nor validation results.

Examples

Specify Options for FIS Tuning

Create a default option set using the particle swarm tuning algorithm.

```
opt = tunefisOptions("Method", "particleswarm")
```

```
opt =
```

```
tunefisOptions with properties:
```

```

        Method: "particleswarm"
    MethodOptions: [1x1 optim.options.Particleswarm]
    OptimizationType: "tuning"
        NumMaxRules: Inf

```



```

IgnoreInvalidParameters: 1
  DistanceMetric: "rmse"
    UseParallel: 0
      KFoldValue: 0
        ValidationTolerance: 0.1000
          ValidationWindowSize: 5
            Display: "all"

```

You can modify the options using dot notation. For example, set the maximum number of iterations to 20.

```
opt.MethodOptions.MaxIterations = 20;
```

You can also specify other options when creating the option set. In this example, set the `OptimizationType` to "learning" to learn new rules.

```
opt2 = tunefisOptions("Method", "particleswarm", "OptimizationType", "learning")
```

```
opt2 =
  tunefisOptions with properties:
```

```

          Method: "particleswarm"
    MethodOptions: [1x1 optim.options.Particleswarm]
  OptimizationType: "learning"
        NumMaxRules: Inf
IgnoreInvalidParameters: 1
  DistanceMetric: "rmse"
    UseParallel: 0
      KFoldValue: 0
        ValidationTolerance: 0.1000
          ValidationWindowSize: 5
            Display: "all"

```

See Also

tunefis | getTunableSettings

Introduced in R2019a

VariableSettings

Tunable parameter settings of fuzzy variables

Description

A `VariableSettings` object contains tunable parameter settings for either an input or output variable of a fuzzy inference system. Using this object, you can specify the tunability settings for the membership functions of the corresponding variable.

Creation

Create a `VariableSettings` object using the `getTunableSettings` function. The first and second outputs of `getTunableSettings` contain `VariableSettings` objects for input and output variables, respectively.

Properties

FISName — Name of fuzzy inference system

string

This property is read-only.

Name of fuzzy inference system, specified as a string.

Type — Type of variable

"input" | "output"

This property is read-only.

Type of variable, specified as either "input" or "output" for input and output variables, respectively.

VariableName — Name of variable

string

This property is read-only.

Name of variable, specified as a string.

MembershipFunctions — Membership function settings

MembershipFunctionSettings object | MembershipFunctionSettingsType2 object

Membership function settings, specified as one of the following:

- `MembershipFunctionSettings` object when the corresponding variable contains type-1 membership functions
- `MembershipFunctionSettingsType2` object when the corresponding variable contains type-2 membership functions

Object Functions

setTunable Set specified parameter settings as tunable or nontunable

Examples

Obtain Tunable Settings of Input and Output Variables from FIS

Create two fuzzy inference systems, and define the connection between the two.

```

fis1 = mamfis('Name', 'fis1', 'NumInputs', 2, 'NumOutputs', 1);
fis2 = sugfis('Name', 'fis2', 'NumInputs', 2, 'NumOutputs', 1);
con = ["fis1/output1" "fis2/input1"];

```

Create a tree of fuzzy inference systems.

```
tree = fistree([fis1 fis2], con);
```

Obtain the tunable settings of input and output variables of the fuzzy inference system.

```
[in, out] = getTunableSettings(tree)
```

```

in=4x1 object
  4x1 VariableSettings array with properties:

```

```

    Type
    VariableName
    MembershipFunctions
    FISName

```

```

out=2x1 object
  2x1 VariableSettings array with properties:

```

```

    Type
    VariableName
    MembershipFunctions
    FISName

```

You can use dot notation to specify the tunable settings of input and output variables.

For the first membership function of input 1, set the first and third parameters to tunable.

```
in(1).MembershipFunctions(1).Parameters.Free = [1 0 1];
```

For the first membership function of input 2, set the minimum parameter range to 0.

```
in(2).MembershipFunctions(1).Parameters.Minimum = 0;
```

For the first membership function of output 2, set the maximum parameter range to 1.

```
out(2).MembershipFunctions(1).Parameters.Maximum = 1;
```

See Also

getTunableSettings | MembershipFunctionSettings |
MembershipFunctionSettingsType2 | RuleSettings

Introduced in R2019a

Blocks

Diff. Sigmoidal MF

Difference of two sigmoids membership function

Library: Fuzzy Logic Toolbox / Membership Functions



Description

The Diff. Sigmoidal MF block implements a membership function in Simulink based on the difference between two sigmoids. The sigmoid curves are defined by the following equation.

$$f(x; a_k, c_k) = \frac{1}{1 + e^{-a_k(x - c_k)}}$$

where $k = 1, 2$. The parameters a_1 and a_2 control the slopes of the left and right curves. The parameters c_1 and c_2 control the points of inflection for the left and right curves.

To define a unimodal membership function with a maximum value of 1, specify the same signs for a_1 and a_2 , and select c values far enough apart to allow for both transition areas to reach 1.

This block is related to the Sigmoidal MF and Prod. Sigmoidal MF membership function blocks.

Ports

Input

x — Input value

scalar | vector

Input value for which to compute membership values, specified as a scalar or vector.

Output

MF — Membership value

scalar | vector

Membership value, returned as a scalar or a vector. The dimensions of **MF** match the dimensions of **x**. Each element of **MF** is the membership value computed for the corresponding element of **x**.

Parameters

Left curve a1 — Transition area shape parameter for left curve

3 (default) | scalar

Parameter a_1 that controls the transition area shape for the left curve. The magnitude of a_1 controls the width of the transition area.

When the sign of a_1 is positive, the curve increases from left to right. Conversely, when the sign of a_1 is negative, the curve decreases from left to right.

Programmatic Use**Block Parameter:** a1**Type:** string, character vector**Default:** "3"**Left curve c1 — Transition area center for left curve**

-5 (default) | scalar

Transition area center c_1 for the left curve.**Programmatic Use****Block Parameter:** c1**Type:** string, character vector**Default:** "-5"**Right curve a2 — Transition area shape parameter for right curve**

1 (default) | scalar

Parameter a_2 that controls the transition area shape for the right curve. The magnitude of a_2 controls the width of the transition area.When the sign of a_2 is positive, the curve increases from left to right. Conversely, when the sign of a_2 is negative, the curve decreases from left to right.**Programmatic Use****Block Parameter:** a2**Type:** string, character vector**Default:** "1"**Right curve c2 — Transition area center for right curve**

5 (default) | scalar

Transition area center c_2 for the right curve.**Programmatic Use****Block Parameter:** c2**Type:** string, character vector**Default:** "5"**Extended Capabilities****C/C++ Code Generation**

Generate C and C++ code using Simulink® Coder™.

PLC Code Generation

Generate Structured Text code using Simulink® PLC Coder™.

See Also**Functions**

dsigmf

Topics


"Membership Functions" on page 1-9

Introduced before R2006a

Fuzzy Logic Controller

Evaluate fuzzy inference system

Library: Fuzzy Logic Toolbox



Description

The Fuzzy Logic Controller block implements a fuzzy inference system (FIS) in Simulink. You specify the FIS to evaluate using the **FIS name** parameter.

For more information on fuzzy inference, see “Fuzzy Inference Process” on page 1-19.

To display the fuzzy inference process in the Rule Viewer during simulation, use the Fuzzy Logic Controller with Ruleviewer block.

Ports

Input

in — Input signal

scalar | vector

For a single-input fuzzy inference system, the input is a scalar signal. For a multi-input fuzzy system, combine the inputs into a vector signal using blocks such as:

- Mux
- Vector Concatenate
- Bus Creator

Output

out — Defuzzified output signal

scalar | vector

For a single-output FIS, the output is a scalar signal. For a multi-output FIS, the output is a vector signal. To split system outputs into scalar signals, use the Demux block.

fi — Fuzzified input values

matrix

Fuzzified input values, obtained by evaluating the input membership functions of each rule at the current input values.

For a type-1 FIS, **fi** is an N_R -by- N_U matrix signal, where N_R is the number of FIS rules. Element (i,j) of **fi** is the value of the input membership function for the j th input in the i th rule.

For a type-2 FIS, **fi** is an N_R -by- $(2*N_U)$ matrix signal. The first N_U columns contain the fuzzified values of the upper membership function for each rule, and the last N_U columns contain the fuzzified values from the lower membership functions.

For more information on fuzzifying input values, see “Fuzzify Inputs” on page 1-20.

Dependencies

To enable this port, select the **Fuzzified inputs (fi)** parameter.

rfs — Rule firing strengths

column vector

Rule firing strengths, obtained by evaluating the antecedent of each rule; that is, applying the fuzzy operator to the values of the fuzzified inputs.

For a type-1 FIS, **rfs** is a column vector signal of length N_R , where N_R is the number of rules, and element i is the firing strength of the i th rule.

For a type-2 FIS, **rfs** is an N_R -by-2 matrix signal. The first column contains the rule firing strengths generated using upper membership functions, and the second column contains the rule firing strengths generated using lower membership functions.

For more information on applying fuzzy operators, see “Apply Fuzzy Operator” on page 1-20.

Dependencies

To enable this port, select the **Rule firing strengths (rfs)** parameter.

ro — Rule outputs

matrix

Rule outputs, obtained by applying the rule firing strengths to the output membership functions using the implication method specified in the FIS.

For a type-1 Mamdani FIS, **ro** is an N_S -by- (N_R*N_Y) matrix signal, where N_R is the number of rules, N_Y is the number of outputs, and N_S is the number of sample points used for evaluating output variable ranges. Each column of **ro** contains the output fuzzy set for one rule. The first N_R columns contain the rule outputs for the first output variable, the next N_R columns correspond to the second output variable, and so on.

For a type-2 Mamdani FIS, **ro** is an N_S -by- $(2*N_R*N_Y)$ matrix signal. The first N_R*N_Y columns contain the rule outputs generated using upper membership functions, and the last N_R*N_Y columns contain the rule outputs generated using lower membership functions.

For a type-1 Sugeno system, each rule output is a scalar value. In this case, **ro** is an N_R -by- N_Y matrix signal. Element (j,k) of **ro** is the value of the k th output variable for the j th rule.

For a type-2 Sugeno system, **ro** is an N_R -by- $(3*N_Y)$ array. The first N_Y columns contain the rule output levels. The next N_Y columns contain the corresponding rule firing strengths generated using upper membership functions. The last N_Y columns contain the rule firing strengths generated using lower membership functions. For example, in a three-output system, columns 4 and 7 contain the firing strengths for the output levels in column 1.

For more information on fuzzy implication, see “Apply Implication Method” on page 1-21.

Dependencies

- To enable this port, select the **Rule outputs (ro)** parameter.
- To specify N_S , use the **Number of samples for output discretization** parameter.

ao — Aggregated output

matrix | row vector

Aggregate output for each output variable, obtained by combining the corresponding outputs from all the rules using the aggregation method specified in the FIS.

For a type-1 Mamdani fuzzy inference system, the aggregate result for each output variable is a fuzzy set. In this case, **ao** is as an N_S -by- N_Y matrix signal, where N_Y is the number of outputs and N_S is the number of sample points used for evaluating output variable ranges. Each column of **ao** contains the aggregate fuzzy set for one output variable.

For a type-2 Mamdani FIS, the aggregate result for each output variable is a fuzzy set. In this case, **ao** is as an N_S -by- $(2*N_Y)$ matrix signal. The first N_Y columns contain the aggregated outputs generated using upper membership functions, and the last N_Y columns contain the aggregated outputs generated using lower membership functions.

For a type-1 Sugeno system, the aggregate result for each output variable is a scalar value. In this case, **ao** is a row vector of length N_Y , where element k is the sum of the rule outputs for the k th output variable.

For a type-2 Sugeno system, **ao** is an N_R -by- $(3*N_Y)$ array. **aggregatedOut** contains the same data as **ro** with the columns sorted based on the output levels. For example, in a three-output system, when the output levels in column 1 are sorted, the corresponding firing strengths in columns 4 and 7 are adjusted accordingly.

For more information on fuzzy aggregation, see “Aggregate All Outputs” on page 1-22.

Dependencies

- To enable this port, select the **Aggregated outputs (ao)** parameter.
- To specify N_S , use the **Number of samples for output discretization** parameter.

Parameters**General****FIS name — Fuzzy inference system**

mamfis object | sugfis object | mamfistype2 object | sugfistype2 object | file name

Fuzzy inference system to evaluate, specified as one of the following:

- **mamfis** or **sugfis** object — Specify the name of a type-1 FIS object in the MATLAB workspace.
- **mamfistype2** or **sugfistype2** object — Specify the name of a type-2 FIS object in the MATLAB workspace.
- **File name** — Specify the name of a **.fis** file in the current working folder or on the MATLAB path. Including the file extension in the file name is optional.

To save a type-1 fuzzy inference system to a **.fis** file:

- In **Fuzzy Logic Designer** or **Neuro-Fuzzy Designer**, select **File > Export > To File**.
- At the command line, use `writeFIS`.

To save a type-2 fuzzy inference system to a `.fis` file, use `wrtieFIS`.

Programmatic Use

Block Parameter: FIS

Type: string, character vector

Default: `'tipper.fis'`

Number of samples for output discretization — Number of points in output fuzzy sets

101 (default) | integer greater than 1

Number of samples for discretizing the range of output variables, specified as an integer greater than 1. This value corresponds to the number of points in the output fuzzy set for each rule.

To reduce memory usage while evaluating a Mamdani FIS, specify a lower number of samples. Doing so sacrifices the accuracy of the defuzzified output value. Specifying a low number of samples can make the output area for defuzzification zero. In this case, the defuzzified output value is the midpoint of the output variable range.

Note The block ignores this parameter when evaluating a Sugeno FIS.

Programmatic Use

Block Parameter: OutputSampleNumber

Type: string, character vector

Default: `"101"`

Data type — Signal data type

double (default) | single | fixed-point | expression

Signal data type, specified as one of the following:

- `double` — Double-precision signals
- `single` — Single-precision signals
- `fixdt(1,16,0)` — Fixed-point signals with binary point scaling
- `fixdt(1,16,2^0,0)` — Fixed-point signals with slope and bias scaling
- `Expression` — Expression that evaluates to one of these data types

For fixed-point data types, you can configure the signedness, word length, and scaling parameters using the **Data Type Assistant**. For more information, see “Specifying a Fixed-Point Data Type” (Simulink).

Programmatic Use

Block Parameter: DataType

Type: string, character vector

Values: `"double"`, `"single"`, `"fixdt(1,16,0)"`, `"fixdt(1,16,2^0,0)"`

Default: `"double"`

Fuzzified inputs (fi) — Enable fi output port

off (default) | on

Enable output port for accessing intermediate fuzzified input data.

Programmatic Use

Block Parameter: FuzzifiedInputs

Type: string, character vector

Values: "off", "on"

Default: "off"

Rule firing strengths (rfs) – Enable rfs output port

off (default) | on

Enable output port for accessing intermediate rule firing strength data.

Programmatic Use

Block Parameter: RuleFiringStrengths

Type: string, character vector

Values: "off", "on"

Default: "off"

Rule outputs (ro) – Enable ro output port

off (default) | on

Enable output port for accessing intermediate rule output data.

Programmatic Use

Block Parameter: RuleOutputs

Type: string, character vector

Values: "off", "on"

Default: "off"

Aggregated outputs (ao) – Enable ao output port

off (default) | on

Enable output port for accessing intermediate aggregate output data.

Programmatic Use

Block Parameter: AggregatedOutputs

Type: string, character vector

Values: "off", "on"

Default: "off"

Simulate using – Simulation mode

Interpreted execution (default) | Code generation

Simulation mode, specified as one of the following:

- **Interpreted execution** — Simulate fuzzy systems using precompiled MEX files for single and double data types. Using this option reduces the initial compilation time of the model.
- **Code generation** — Simulate fuzzy system without precompiled MEX files. Use this option when simulating fuzzy systems for code generation applications.

For fixed-point data types, the Fuzzy Logic Controller block always simulates using Code generation mode.

Programmatic Use

Block Parameter: SimulateUsing

Type: string, character vector

Values: "Interpreted execution", "Code generation"

Default: "Interpreted execution"

Diagnostics

Out of range input value — Diagnostic message behavior when an input is out of range

warning (default) | error | none

Diagnostic message behavior when an input is out of range, specified as one of the following:

- warning — Report the diagnostic message as a warning.
- error — Report the diagnostic message as an error.
- none — Do not report the diagnostic message.

When an input value is out of range, corresponding rules in the fuzzy system can have unexpected firing strengths.

Dependencies

- Diagnostic messages are provided only when the **Simulate using** parameter is Interpreted execution.

Programmatic Use

Block Parameter: OutOfRangeInputValueMessage

Type: string, character vector

Values: "warning", "error", "none"

Default: "warning"

No rule fired — Diagnostic message behavior when no rules fire

warning (default) | error | none

Diagnostic message behavior when no rules fire for a given output variable, specified as one of the following:

- warning — Report the diagnostic message as a warning.
- error — Report the diagnostic message as an error.
- none — Do not report the diagnostic message.

When **No rule fired** is warning or none and no rules fire for a given output, the defuzzified output value is set to its mean range value.

Dependencies

- Diagnostic messages are provided only when the **Simulate using** parameter is Interpreted execution.

Programmatic Use

Block Parameter: NoRuleFiredMessage

Type: string, character vector

Values: "warning", "error", "none"

Default: "warning"

Empty output fuzzy set — Diagnostic message behavior when an output fuzzy set is empty

warning (default) | error | none

Diagnostic message behavior when an output fuzzy set is empty, specified as one of the following:

- `warning` — Report the diagnostic message as a warning.
- `error` — Report the diagnostic message as an error.
- `none` — Do not report the diagnostic message.

When **Empty output fuzzy set** is `warning` or `none` and an output fuzzy set is empty, the defuzzified value for the corresponding output is set to its mean range value.

Dependencies

- This diagnostic message applies to Mamdani systems only.
- Diagnostic messages are provided only when the **Simulate using** parameter is `Interpreted execution`.

Programmatic Use

Block Parameter: `EmptyOutputFuzzySetMessage`

Type: string, character vector

Values: "warning", "error", "none"

Default: "warning"

Compatibility Considerations

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using Simulink® Coder™.

PLC Code Generation

Generate Structured Text code using Simulink® PLC Coder™.

Fixed-Point Conversion

Design and simulate fixed-point systems using Fixed-Point Designer™.

See Also

Blocks

Fuzzy Logic Controller with Ruleviewer

Apps

Fuzzy Logic Designer | Neuro-Fuzzy Designer

Functions

mamfis | sugfis | mamfistype2 | sugfistype2 | readfis | evalfis | genfis | writeFIS

Topics

“Fuzzy Inference Process” on page 1-19

“Simulate Fuzzy Inference Systems in Simulink” on page 5-2

Introduced before R2006a

Fuzzy Logic Controller with Ruleviewer

Evaluate fuzzy inference system and view rules

Library: Fuzzy Logic Toolbox



Description

The Fuzzy Logic Controller with Ruleviewer block implements a fuzzy inference system (FIS) in Simulink and displays the fuzzy inference process in the Rule Viewer during the simulation. You specify the FIS to evaluate using the **FIS matrix** parameter. To change the time between Rule Viewer updates, specify the **Refresh rate** in seconds.

For more information on fuzzy inference, see “Fuzzy Inference Process” on page 1-19.

The Fuzzy Logic Controller with Ruleviewer block does not support all the features supported by the Fuzzy Logic Controller block. The Fuzzy Logic Controller with Ruleviewer block:

- Only supports double-precision data.
- Uses 101 points for discretizing output variable ranges.
- Only supports Interpreted execution simulation mode.
- Does not have additional output ports for accessing intermediate fuzzy inference results.

Ports

Input

Port_1(In1) — Input signal

scalar | vector

For a single-input fuzzy inference system, the input is a scalar. For a multi-input fuzzy system, combine the inputs into a vector signal using blocks such as:

- Mux
- Vector Concatenate
- Bus Creator

Output

Port_1(Out1) — Defuzzified output signal

scalar | vector

For a single-output fuzzy inference system, the output is a scalar. For a multi-output fuzzy system, the output is a vector. To split system outputs into scalar signals, use the Demux block.

Parameters

FIS structure — Fuzzy inference system

`mamfisobject` | `sugfisobject`

Fuzzy inference system to evaluate, specified as a `mamfis` or `sugfis` object. Specify the name of a FIS object in the MATLAB workspace.

Programmatic Use

Block Parameter: `fismatrix`

Type: string, character vector

Default: "fis"

Refresh rate — Time between rule viewer updates

scalar

Time between rule viewer updates in seconds, specified as a scalar. During simulation, the Rule Viewer display updates at the specified rate to show the inference process for the latest input signal values.

Programmatic Use

Block Parameter: `Ts`

Type: string, character vector

Default: "2"

Compatibility Considerations

Support for representing fuzzy inference systems as structures will be removed

Warns starting in R2019b

Support for representing fuzzy inference systems as structures will be removed in a future release. Use `mamfis` and `sugfis` objects instead. There are differences between these representations that require updates to your code. These differences include:

- Object property names that differ from the corresponding structure fields.
- Objects store text data as strings rather than as character vectors.

Also, all Fuzzy Logic Toolbox functions that accepted or returned fuzzy inference systems as structures now accept and return either `mamfis` or `sugfis` objects.

To convert existing fuzzy inference system structures to objects, use the `convertfis` function.

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using Simulink® Coder™.

Usage notes and limitations:

- Generating code using the Fuzzy Logic Controller with Ruleviewer block produces the same code as using the Fuzzy Logic Controller block. However, the Fuzzy Logic Controller with Ruleviewer block does not support:

- Generating code for single-point or fixed-point data.
- Changing the number of samples for discretizing the output variable range.

See Also

Blocks

Fuzzy Logic Controller

Apps

Fuzzy Logic Designer | **Neuro-Fuzzy Designer**

Functions

mamfis | sugfis | readfis | evalfis

Topics

“Fuzzy Inference Process” on page 1-19

“Simulate Fuzzy Inference Systems in Simulink” on page 5-2

Introduced before R2006a

Gaussian MF

Gaussian membership function

Library: Fuzzy Logic Toolbox / Membership Functions



Description

The Gaussian MF block implements a membership function based on a symmetric Gaussian function.

$$f(x; \sigma, c) = e^{-\frac{(x-c)^2}{2\sigma^2}}$$

Here, c is the mean and σ is the standard deviation of the Gaussian function.

A Gaussian membership function is not the same as a Gaussian probability distribution. For example, a Gaussian membership function always has a maximum value of 1. For more information on Gaussian probability distributions, see “Normal Distribution” (Statistics and Machine Learning Toolbox).

Ports

Input

x — Input value

scalar | vector

Input value for which to compute membership values, specified as a scalar or vector.

Output

MF — Membership value

scalar | vector

Membership value, returned as a scalar or a vector. The dimensions of **MF** match the dimensions of **x**. Each element of **MF** is the membership value computed for the corresponding element of **x**.

Parameters

Standard deviation sigma — Standard deviation

1 (default) | scalar

Standard deviation σ of the Gaussian function.

Programmatic Use

Block Parameter: sigma

Type: string, character vector

Default: "1"

Mean c — Mean

0 (default) | scalar

Mean c of the Gaussian function.

Programmatic Use

Block Parameter: mu

Type: string, character vector

Default: "0"

Extended Capabilities**C/C++ Code Generation**

Generate C and C++ code using Simulink® Coder™.

PLC Code Generation

Generate Structured Text code using Simulink® PLC Coder™.

See Also**Functions**

gaussmf

Blocks

Diff. Sigmoidal MF | Gaussian2 MF | Generalized Bell MF | Linear S-shaped MF | Linear Z-shaped MF
| Pi-shaped MF | Prod. Sigmoidal MF | S-shaped MF | Sigmoidal MF | Trapezoidal MF | Triangular MF
| Z-shaped MF

Topics

"Membership Functions" on page 1-9

Introduced before R2006a

Gaussian2 MF

Combination of two Gaussian membership functions

Library: Fuzzy Logic Toolbox / Membership Functions



Description

The Gaussian2 MF block implements a membership function based on a combination of two Gaussian functions. The two Gaussian functions are given by the following equation.

$$f(x; \sigma_k, c_k) = e^{-\frac{(x - c_k)^2}{2\sigma_k^2}}$$

where $k = 1, 2$. The parameters c_1 and σ_1 are the mean and standard deviation defining the left-most curve. The parameters c_2 and σ_2 are the mean and standard deviation defining the right-most curve.

Ports

Input

x — Input value

scalar | vector

Input value for which to compute membership values, specified as a scalar or vector.

Output

MF — Membership value

scalar | vector

Membership value, returned as a scalar or a vector. The dimensions of **MF** match the dimensions of **x**. Each element of **MF** is the membership value computed for the corresponding element of **x**.

When $c_1 \leq c_2$, the membership function reaches a maximum value of 1 over the range $[c_1, c_2]$.

Otherwise, when $c_1 > c_2$, the maximum value is less than one.

Parameters

Standard deviation for left curve sigma1 — Left Gaussian standard deviation

3 (default) | scalar

Standard deviation σ_1 of the left Gaussian function.

Programmatic Use

Block Parameter: sigma1

Type: string, character vector

Default: "3"

Mean for left curve c1 – Left Gaussian mean

-1 (default) | scalar

Mean c_1 of the left Gaussian function.

Programmatic Use

Block Parameter: mu1

Type: string, character vector

Default: "-1"

Standard deviation for right curve sigma2 – Right Gaussian standard deviation

1 (default) | scalar

Standard deviation σ_2 of the right Gaussian function.

Programmatic Use

Block Parameter: sigma2

Type: string, character vector

Default: "1"

Mean for right curve c2 – Right Gaussian mean

5 (default) | scalar

Mean c_2 of the right Gaussian function.

Programmatic Use

Block Parameter: mu2

Type: string, character vector

Default: "5"

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using Simulink® Coder™.

PLC Code Generation

Generate Structured Text code using Simulink® PLC Coder™.

See Also

Functions

gauss2mf

Blocks

Diff. Sigmoidal MF | Gaussian MF | Generalized Bell MF | Linear S-shaped MF | Linear Z-shaped MF | Pi-shaped MF | Prod. Sigmoidal MF | S-shaped MF | Sigmoidal MF | Trapezoidal MF | Triangular MF | Z-shaped MF

Topics

"Membership Functions" on page 1-9

Introduced before R2006a

Generalized Bell MF

Generalized bell membership function

Library: Fuzzy Logic Toolbox / Membership Functions



Description

The Generalized Bell MF block implements a membership function based on a generalized bell-shaped function.

$$f(x; a, b, c) = \frac{1}{1 + \left| \frac{x-c}{a} \right|^{2b}}$$

Here, a and b control the width of the function and c controls the center of the function.

Ports

Input

x — Input value

scalar | vector

Input value for which to compute membership values, specified as a scalar or vector.

Output

MF — Membership value

scalar | vector

Membership value, returned as a scalar or a vector. The dimensions of **MF** match the dimensions of **x**. Each element of **MF** is the membership value computed for the corresponding element of **x**.

Parameters

a — Function shape parameter

5 (default) | scalar

Parameter that, together with **b**, defines the shape of the membership function.

Programmatic Use

Block Parameter: a

Type: string, character vector

Default: "5"

b — Function shape parameter

4 (default) | positive scalar

Parameter that, together with **a**, defines the shape of the membership function.

Programmatic Use**Block Parameter:** b**Type:** string, character vector**Default:** "4"**c — Center point** θ (default) | scalar

Function center point.

Programmatic Use**Block Parameter:** c**Type:** string, character vector**Default:** "0"**Extended Capabilities****C/C++ Code Generation**

Generate C and C++ code using Simulink® Coder™.

PLC Code Generation

Generate Structured Text code using Simulink® PLC Coder™.

See Also**Functions**

gbellmf

Blocks

Diff. Sigmoidal MF | Gaussian MF | Gaussian2 MF | Linear S-shaped MF | Linear Z-shaped MF | Pi-shaped MF | Prod. Sigmoidal MF | S-shaped MF | Sigmoidal MF | Trapezoidal MF | Triangular MF | Z-shaped MF

Topics

"Membership Functions" on page 1-9

Introduced before R2006a

Linear S-shaped MF

Linear s-shaped saturation membership function

Library: Fuzzy Logic Toolbox / Membership Functions



Description

The Linear S-Shaped MF block implements a linear s-shaped saturation membership function.

- When $a < b$:

$$f(x; a, b) = \begin{cases} 0, & x < a \\ \frac{x-a}{b-a}, & a \leq x \leq b \\ 1, & x > b \end{cases}$$

- When $a = b$:

$$f(x; a, b) = \begin{cases} 0, & x < a \\ 1, & x \geq a \end{cases}$$

The parameters a and b control the foot and shoulder of the membership function, respectively. Setting a equal to b produces a crisp membership function.

This block is related to the Triangular MF, Trapezoidal MF, and Linear Z-shaped MF blocks.

Ports

Input

x — Input value

scalar | vector

Input value for which to compute membership values, specified as a scalar or vector.

Output

MF — Membership value

scalar | vector

Membership value, returned as a scalar or a vector. The dimensions of **MF** match the dimensions of **x**. Each element of **MF** is the membership value computed for the corresponding element of **x**.

Parameters

Left point a — Leftmost point of transition area

4 (default) | scalar

Leftmost point a of the transition area.

Programmatic Use

Block Parameter: a

Type: string, character vector

Default: "4"

Right point b — Rightmost point of transition area

6 (default) | scalar

Rightmost point b of the transition area.

Programmatic Use

Block Parameter: b

Type: string, character vector

Default: "6"

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using Simulink® Coder™.

PLC Code Generation

Generate Structured Text code using Simulink® PLC Coder™.

See Also

Functions

linsmf

Blocks

Diff. Sigmoidal MF | Gaussian MF | Gaussian2 MF | Generalized Bell MF | Linear Z-shaped MF | Pi-shaped MF | Prod. Sigmoidal MF | S-shaped MF | Sigmoidal MF | Trapezoidal MF | Triangular MF | Z-shaped MF

Topics

"Membership Functions" on page 1-9

Introduced in R2022a

Linear Z-shaped MF

Linear z-shaped saturation membership function

Library: Fuzzy Logic Toolbox / Membership Functions



Description

The Linear Z-Shaped MF block implements a linear z-shaped saturation membership function.

- When $a < b$:

$$f(x; a, b) = \begin{cases} 1, & x < a \\ \frac{a-x}{a-b}, & a \leq x \leq b \\ 0, & x > b \end{cases}$$

- When $a = b$:

$$f(x; a, b) = \begin{cases} 1, & x < a \\ 0, & x \geq a \end{cases}$$

The parameters a and b control the shoulder and foot of the membership function, respectively. Setting a equal to b produces a crisp membership function.

This block is related to the Triangular MF, Trapezoidal MF, and Linear S-shaped MF blocks.

Ports

Input

x — Input value

scalar | vector

Input value for which to compute membership values, specified as a scalar or vector.

Output

MF — Membership value

scalar | vector

Membership value, returned as a scalar or a vector. The dimensions of **MF** match the dimensions of **x**. Each element of **MF** is the membership value computed for the corresponding element of **x**.

Parameters

Left point a — Leftmost point of transition area

4 (default) | scalar

Leftmost point a of the transition area.

Programmatic Use

Block Parameter: a

Type: string, character vector

Default: "4"

Right point b — Rightmost point of transition area

6 (default) | scalar

Rightmost point b of the transition area.

Programmatic Use

Block Parameter: b

Type: string, character vector

Default: "6"

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using Simulink® Coder™.

PLC Code Generation

Generate Structured Text code using Simulink® PLC Coder™.

See Also

Functions

linzmf

Blocks

Diff. Sigmoidal MF | Gaussian MF | Gaussian2 MF | Generalized Bell MF | Linear S-shaped MF | Pi-shaped MF | Prod. Sigmoidal MF | S-shaped MF | Sigmoidal MF | Trapezoidal MF | Triangular MF | Z-shaped MF

Topics

"Membership Functions" on page 1-9

Introduced in R2022a

Pi-shaped MF

Pi-shaped membership function

Library: Fuzzy Logic Toolbox / Membership Functions



Description

The Pi-shaped MF block implements a pi-shaped membership function.

$$f(x; a, b, c, d) = \begin{cases} 0, & x \leq a \\ 2\left(\frac{x-a}{b-a}\right)^2, & a \leq x \leq \frac{a+b}{2} \\ 1-2\left(\frac{x-b}{b-a}\right)^2, & \frac{a+b}{2} \leq x \leq b \\ 1, & b \leq x \leq c \\ 1-2\left(\frac{x-c}{d-c}\right)^2, & c \leq x \leq \frac{c+d}{2} \\ 2\left(\frac{x-d}{d-c}\right)^2, & \frac{c+d}{2} \leq x \leq d \\ 0, & x \geq d \end{cases}$$

The parameters a and d control the left and right base points or *feet* of the curve. The parameters b and c control the left and right top points or *shoulders* of the curve.

This block is related to the Z-shaped MF and S-shaped MF blocks.

Ports

Input

x — Input value

scalar | vector

Input value for which to compute membership values, specified as a scalar or vector.

Output

Pi MF — Membership value

scalar | vector

Membership value, returned as a scalar or a vector. The dimensions of **Pi MF** match the dimensions of **x**. Each element of **Pi MF** is the membership value computed for the corresponding element of **x**.

Parameters

Left base point a — Foot of left transition area

-9 (default) | scalar

Foot a of the left transition area.

Programmatic Use

Block Parameter: a

Type: string, character vector

Default: "-9"

Left top point b — Shoulder of left transition area

-7 (default) | scalar

Shoulder b of the left transition area.

Programmatic Use

Block Parameter: b

Type: string, character vector

Default: "-7"

Right top point c — Shoulder of right transition area

-9 (default) | scalar

Shoulder c of the right transition area.

Programmatic Use

Block Parameter: c

Type: string, character vector

Default: "2"

Right base point d — Foot of right transition area

-7 (default) | scalar

Foot d of the right transition area.

Programmatic Use

Block Parameter: d

Type: string, character vector

Default: "8"

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using Simulink® Coder™.

PLC Code Generation

Generate Structured Text code using Simulink® PLC Coder™.

See Also

Functions

pimf

Blocks

Diff. Sigmoidal MF | Gaussian MF | Gaussian2 MF | Generalized Bell MF | Linear S-shaped MF |
Linear Z-shaped MF | Prod. Sigmoidal MF | S-shaped MF | Sigmoidal MF | Trapezoidal MF |
Triangular MF | Z-shaped MF

Topics

“Membership Functions” on page 1-9

Introduced before R2006a

Probabilistic OR

Probabilistic OR function

Library: Fuzzy Logic Toolbox / Membership Functions



Description

The Probabilistic OR block returns the probabilistic OR value, or algebraic sum, for the input signal.

Ports

Input

In1 — Input values

array | row vector

Input values, specified as an array or row vector x .

Output

Out1 — Probabilistic OR values

row vector

Probabilistic OR values, returned as a row vector y with the same number of columns as the input x . Each element of y contains the probabilistic OR value for the corresponding column in x .

If x has one row, then $y = x$.

If $x = [A; B]$, where A and B are row vectors, then the i th element of y is the following algebraic sum.

$$y(i) = A(i) + B(i) - A(i)*B(i);$$

If x has more than two rows, the probabilistic OR is initially calculated for the first two rows. Then, the probabilistic OR is computed between the result and the next row. This process repeats for each subsequent row.

$$\begin{aligned} x &= [A; B; C; D] \\ y(i) &= A(i) + B(i) - A(i)*B(i); \\ y(i) &= y(i) + C(i) - y(i)*C(i); \\ y(i) &= y(i) + D(i) - y(i)*D(i); \end{aligned}$$

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using Simulink® Coder™.

PLC Code Generation

Generate Structured Text code using Simulink® PLC Coder™.

See Also

Blocks

Probabilistic Rule Agg

Functions

probor

Introduced before R2006a

Probabilistic Rule Agg

Probabilistic OR function for rule aggregation

Library: Fuzzy Logic Toolbox / Membership Functions



Description

The Probabilistic Rule Agg block returns the element-wise probabilistic OR, or algebraic sum, of the two input vectors.

Ports

Input

In1 — Input values

row vector

Input values, specified as a row vector with the same number of elements as **In2**.

In2 — Input values

row vector

Input values, specified as a row vector with the same number of elements as **In1**.

Output

Out1 — Probabilistic OR values

row vector

Probabilistic OR values, returned as a row vector y with the same number of elements as both **In1** and **In2**. Each element of y contains the probabilistic OR of the corresponding elements from the input vectors.

Let $A = \mathbf{In1}$ and $B = \mathbf{In2}$. Then, the probabilistic OR of the i th elements of the input vectors is the following algebraic sum.

$$y(i) = A(i) + B(i) - A(i)*B(i);$$

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using Simulink® Coder™.

PLC Code Generation

Generate Structured Text code using Simulink® PLC Coder™.

See Also

Blocks

Probabilistic OR

Functions

probor

Introduced before R2006a

Prod. Sigmoidal MF

Product of two sigmoid membership functions

Library: Fuzzy Logic Toolbox / Membership Functions



Description

The Prod. Sigmoidal MF block implements a membership function based on the product of two sigmoidal curves. The sigmoidal curves are defined by the following equation.

$$f(x; a_k, c_k) = \frac{1}{1 + e^{-a_k(x - c_k)}}$$

where $k = 1, 2$. The parameters a_1 and a_2 control the slopes of the left and right curves. The parameters c_1 and c_2 control the points of inflection for the left and right curves.

To define a unimodal membership function with a maximum value of 1, specify opposite signs for a_1 and a_2 , and select c values far enough apart to allow for both transition areas to reach 1.

This block is related to the Diff. Sigmoidal MF and Sigmoidal MF blocks.

Ports

Input

x — Input value

scalar | vector

Input value for which to compute membership values, specified as a scalar or vector.

Output

MF — Membership value

scalar | vector

Membership value, returned as a scalar or a vector. The dimensions of **MF** match the dimensions of **x**. Each element of **MF** is the membership value computed for the corresponding element of **x**.

Parameters

Left curve a1 — Transition area shape parameter for left curve

2 (default) | scalar

Parameter a_1 that controls the transition area shape for the left curve. The magnitude of a_1 controls the width of the transition area.

When the sign of a_1 is positive, the curve increases from left to right. Conversely, when the sign of a_1 is negative, the curve decreases from left to right.

Programmatic Use**Block Parameter:** a1**Type:** string, character vector**Default:** "2"**Left curve c1 — Transition area center for left curve**

-5 (default) | scalar

Transition area center c_1 for the left curve.**Programmatic Use****Block Parameter:** c1**Type:** string, character vector**Default:** "-5"**Right curve a2 — Transition area shape parameter for right curve**

-5 (default) | scalar

Parameter a_2 that controls the transition area shape for the right curve. The magnitude of a_2 controls the width of the transition area.

When the sign of a_2 is positive, the curve increases from left to right. Conversely, when the sign of a_2 is negative, the curve decreases from left to right.

Programmatic Use**Block Parameter:** a2**Type:** string, character vector**Default:** "-5"**Right curve c2 — Transition area center for right curve**

5 (default) | scalar

Transition area center c_2 for the right curve.**Programmatic Use****Block Parameter:** c2**Type:** string, character vector**Default:** "5"

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using Simulink® Coder™.

PLC Code Generation

Generate Structured Text code using Simulink® PLC Coder™.

See Also

Functions

psigmf

Blocks

Diff. Sigmoidal MF | Gaussian MF | Gaussian2 MF | Generalized Bell MF | Linear S-shaped MF |
Linear Z-shaped MF | Pi-shaped MF | S-shaped MF | Sigmoidal MF | Trapezoidal MF | Triangular MF
| Z-shaped MF

Topics

“Membership Functions” on page 1-9

Introduced before R2006a

S-shaped MF

S-shaped membership function

Library: Fuzzy Logic Toolbox / Membership Functions



Description

The S-shaped MF block implements an s-shaped membership function.

$$f(x; a, b) = \begin{cases} 0, & x \leq a \\ 2\left(\frac{x-a}{b-a}\right)^2, & a \leq x \leq \frac{a+b}{2} \\ 1-2\left(\frac{x-b}{b-a}\right)^2, & \frac{a+b}{2} \leq x \leq b \\ 1, & x \geq b \end{cases}$$

Going from left to right the function increases from 0 to 1. The parameters a and b control the left and right extremes of the sloped portion of the curve.

This block is related to the Z-shaped MF and Pi-shaped MF blocks.

Ports

Input

x — Input value

scalar | vector

Input value for which to compute membership values, specified as a scalar or vector.

Output

S MF — Membership value

scalar | vector

Membership value, returned as a scalar or a vector. The dimensions of **S MF** match the dimensions of **x**. Each element of **S MF** is the membership value computed for the corresponding element of **x**.

Parameters

Left point a — Leftmost point of transition area

-3 (default) | scalar

Leftmost point a of the transition area.

Programmatic Use**Block Parameter:** a**Type:** string, character vector**Default:** "-3"**Right point b — Rightmost point of transition area**

3 (default) | scalar

Rightmost point *b* of the transition area.**Programmatic Use****Block Parameter:** b**Type:** string, character vector**Default:** "3"**Extended Capabilities****C/C++ Code Generation**

Generate C and C++ code using Simulink® Coder™.

PLC Code Generation

Generate Structured Text code using Simulink® PLC Coder™.

See Also**Functions**

smf

Blocks

Diff. Sigmoidal MF | Gaussian MF | Gaussian2 MF | Generalized Bell MF | Linear S-shaped MF | Linear Z-shaped MF | Pi-shaped MF | Prod. Sigmoidal MF | Sigmoidal MF | Trapezoidal MF | Triangular MF | Z-shaped MF

Topics

"Membership Functions" on page 1-9

Introduced before R2006a

Sigmoidal MF

Sigmoidal membership function

Library: Fuzzy Logic Toolbox / Membership Functions



Description

The Sigmoidal MF block implements a sigmoidal membership function.

$$f(x; a, c) = \frac{1}{1 + e^{-a(x - c)}}$$

When the sign of a is positive, the curve increases from left to right. Conversely, when the sign of a is negative, the curve decreases from left to right. The parameter c sets the point of inflection for the curve.

This block is related to the Diff. Sigmoidal MF and Prod. Sigmoidal MF blocks.

Ports

Input

x — Input value

scalar | vector

Input value for which to compute membership values, specified as a scalar or vector.

Output

MF — Membership value

scalar | vector

Membership value, returned as a scalar or a vector. The dimensions of **MF** match the dimensions of **x**. Each element of **MF** is the membership value computed for the corresponding element of **x**.

Parameters

a — Transition area shape parameter

1 (default) | scalar

Parameter that controls the transition area shape. The magnitude of **a** controls the width of the transition area.

When the sign of **a** is positive, the curve increases from left to right. Conversely, when the sign of **a** is negative, the curve decreases from left to right.

Programmatic Use**Block Parameter:** a**Type:** string, character vector**Default:** "1"**c — Transition area center**

0 (default) | scalar

Transition area center.

Programmatic Use**Block Parameter:** c**Type:** string, character vector**Default:** "0"**Extended Capabilities****C/C++ Code Generation**

Generate C and C++ code using Simulink® Coder™.

PLC Code Generation

Generate Structured Text code using Simulink® PLC Coder™.

See Also**Functions**

sigmf

Blocks

Diff. Sigmoidal MF | Gaussian MF | Gaussian2 MF | Generalized Bell MF | Linear S-shaped MF | Linear Z-shaped MF | Pi-shaped MF | Prod. Sigmoidal MF | S-shaped MF | Trapezoidal MF | Triangular MF | Z-shaped MF

Topics

"Membership Functions" on page 1-9

Introduced before R2006a

Trapezoidal MF

Trapezoidal membership function

Library: Fuzzy Logic Toolbox / Membership Functions



Description

The Trapezoidal MF block implements a trapezoid-shaped membership function.

$$f(x; a, b, c, d) = \max\left(\min\left(\frac{x-a}{b-a}, 1, \frac{d-x}{d-c}\right), 0\right)$$

The parameters a and d control the left and right *feet* or base points of the trapezoid. The parameters b and c control the left and right *shoulders* or top points of the trapezoid.

The shape of the membership function depends on the relative values of b and c .

- When c is greater than b , the resulting membership function is trapezoidal.
- When b is equal to c , the resulting membership function is equivalent to a triangular membership function with parameters $[a \ b \ d]$.
- When c is less than b , the resulting membership function is triangular with a maximum value less than 1.

This block is related to the Triangular MF, Linear S-shaped MF, and Linear Z-shaped MF blocks.

Ports

Input

x — Input value

scalar | vector

Input value for which to compute membership values, specified as a scalar or vector.

Output

MF — Membership value

scalar | vector

Membership value, returned as a scalar or a vector. The dimensions of **MF** match the dimensions of **x**. Each element of **MF** is the membership value computed for the corresponding element of **x**.

Parameters

Left base point a — Left foot of trapezoid

-8 (default) | scalar

Left foot a of the trapezoid.

Programmatic Use

Block Parameter: a

Type: string, character vector

Default: "-8"

Left top point b – Left shoulder of trapezoid

-4 (default) | scalar

Left shoulder b of the trapezoid.

Programmatic Use

Block Parameter: b

Type: string, character vector

Default: "-4"

Right top point c – Right shoulder of trapezoid

2 (default) | scalar

Right shoulder c of the trapezoid.

Programmatic Use

Block Parameter: c

Type: string, character vector

Default: "2"

Right base point d – Right foot of trapezoid

9 (default) | scalar

Right foot d of the trapezoid.

Programmatic Use

Block Parameter: d

Type: string, character vector

Default: "9"

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using Simulink® Coder™.

PLC Code Generation

Generate Structured Text code using Simulink® PLC Coder™.

See Also

Functions

trapmf

Blocks

Diff. Sigmoidal MF | Gaussian MF | Gaussian2 MF | Generalized Bell MF | Linear S-shaped MF | Linear Z-shaped MF | Pi-shaped MF | Prod. Sigmoidal MF | S-shaped MF | Sigmoidal MF | Triangular MF | Z-shaped MF

Topics

“Membership Functions” on page 1-9

Introduced before R2006a

Triangular MF

Triangular membership function

Library: Fuzzy Logic Toolbox / Membership Functions



Description

The Triangular MF block implements a triangle-shaped membership function.

$$f(x; a, b, c) = \begin{cases} 0, & x \leq a \\ \frac{x-a}{b-a}, & a \leq x \leq b \\ \frac{c-x}{c-b}, & b \leq x \leq c \\ 0, & c \leq x \end{cases}$$

More compactly, the function is as follows.

$$f(x; a, b, c) = \max\left(\min\left(\frac{x-a}{b-a}, \frac{c-x}{c-b}\right), 0\right)$$

The parameters a and c set the left and right *feet* or base points of the triangle. The parameter b sets the location of the triangle peak.

This block is related to the Trapezoidal MF, Linear S-shaped MF, and Linear Z-shaped MF blocks.

Ports

Input

x — Input value

scalar | vector

Input value for which to compute membership values, specified as a scalar or vector.

Output

MF — Membership value

scalar | vector

Membership value, returned as a scalar or a vector. The dimensions of **MF** match the dimensions of **x**. Each element of **MF** is the membership value computed for the corresponding element of **x**.

Parameters

Left base point a — Left foot of triangle

1 (default) | scalar

Left foot a of the triangle.

Programmatic Use**Block Parameter:** a**Type:** string, character vector**Default:** "1"**Peak location b — Triangle peak**

3 (default) | scalar

Triangle peak b .

Programmatic Use**Block Parameter:** b**Type:** string, character vector**Default:** "3"**Right base point c — Right foot of triangle**

6 (default) | scalar

Right foot c of the triangle.

Programmatic Use**Block Parameter:** c**Type:** string, character vector**Default:** "6"

Extended Capabilities

C/C++ Code Generation

Generate C and C++ code using Simulink® Coder™.

PLC Code Generation

Generate Structured Text code using Simulink® PLC Coder™.

See Also

Functions

trimf

Blocks

Diff. Sigmoidal MF | Gaussian MF | Gaussian2 MF | Generalized Bell MF | Linear S-shaped MF | Linear Z-shaped MF | Pi-shaped MF | Prod. Sigmoidal MF | S-shaped MF | Sigmoidal MF | Trapezoidal MF | Z-shaped MF

Topics

"Membership Functions" on page 1-9

Introduced before R2006a

Z-shaped MF

Z-shaped membership function

Library: Fuzzy Logic Toolbox / Membership Functions



Description

The Z-shaped MF block implements a z-shaped membership function.

$$f(x; a, b) = \begin{cases} 1, & x \leq a \\ 1 - 2\left(\frac{x-a}{b-a}\right)^2, & a \leq x \leq \frac{a+b}{2} \\ 2\left(\frac{x-b}{b-a}\right)^2, & \frac{a+b}{2} \leq x \leq b \\ 0 & x \geq b \end{cases}$$

Going from left to right the function decreases from 1 to 0. The parameters a and b control the left and right extremes of the sloped portion of the curve.

This block is related to the S-shaped MF and Pi-shaped MF blocks.

Ports

Input

x — Input value

scalar | vector

Input value for which to compute membership values, specified as a scalar or vector.

Output

Z MF — Membership value

scalar | vector

Membership value, returned as a scalar or a vector. The dimensions of **Z MF** match the dimensions of **x**. Each element of **Z MF** is the membership value computed for the corresponding element of **x**.

Parameters

Left point a — Leftmost point of transition area

-3 (default) | scalar

Leftmost point a of the transition area.

Programmatic Use**Block Parameter:** a**Type:** string, character vector**Default:** "-3"**Right point b — Rightmost point of transition area**

3 (default) | scalar

Rightmost point *b* of the transition area.**Programmatic Use****Block Parameter:** b**Type:** string, character vector**Default:** "3"**Extended Capabilities****C/C++ Code Generation**

Generate C and C++ code using Simulink® Coder™.

PLC Code Generation

Generate Structured Text code using Simulink® PLC Coder™.

See Also**Functions**

zmf

Blocks

Diff. Sigmoidal MF | Gaussian MF | Gaussian2 MF | Generalized Bell MF | Linear S-shaped MF | Linear Z-shaped MF | Pi-shaped MF | Prod. Sigmoidal MF | S-shaped MF | Sigmoidal MF | Trapezoidal MF | Triangular MF

Topics

"Membership Functions" on page 1-9

Introduced before R2006a