
Mapping Toolbox™

User's Guide



MATLAB®



How to Contact MathWorks



Latest news: www.mathworks.com

Sales and services: www.mathworks.com/sales_and_services

User community: www.mathworks.com/matlabcentral

Technical support: www.mathworks.com/support/contact_us

T

Phone: 508-647-7000



The MathWorks, Inc. 1 Apple Hill Drive Natick, MA 01760-2098

Mapping Toolbox™ User's Guide

© COPYRIGHT 1997-2022 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See www.mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

Patents

MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

Revision History

May 1997 First printing New for Version 1.0 October 1998 Second printing Version 1.1 November 2000 Third printing Version 1.2 (Release 12) Online only Revised for Version 1.3 (Release 13) July 2002 September 2003 Online only Revised for Version 1.3.1 (Release 13SP1) January 2004 Online only Revised for Version 2.0 (Release 13SP1+) April 2004 Online only Revised for Version 2.0.1 (Release 13SP1+) Fourth printing Revised for Version 2.0.2 (Release 14) **June 2004** October 2004 Online only Revised for Version 2.0.3 (Release 14SP1) March 2005 Fifth printing Revised for Version 2.1 (Release 14SP2) August 2005 Sixth printing Minor revision for Version 2.1 September 2005 Online only Revised for Version 2.2 (Release 14SP3) March 2006 Online only Revised for Version 2.3 (Release 2006a) September 2006 Seventh printing Revised for Version 2.4 (Release 2006b) March 2007 Online only Revised for Version 2.5 (Release 2007a) September 2007 Eighth printing Revised for Version 2.6 (Release 2007b) Revised for Version 2.7 (Release 2008a) March 2008 Online only Online only Revised for Version 2.7.1 (Release 2008b) October 2008 Revised for Version 2.7.2 (Release 2009a) March 2009 Online only September 2009 Online only Revised for Version 3.0 (Release 2009b) March 2010 Online only Revised for Version 3.1 (Release 2010a) September 2010 Online only Revised for Version 3.2 (Release 2010b) Online only Revised for Version 3.3 (Release 2011a) April 2011 September 2011 Online only Revised for Version 3.4 (Release 2011b) March 2012 Online only Revised for Version 3.5 (Release 2012a) September 2012 Online only Revised for Version 3.6 (Release 2012b) March 2013 Online only Revised for Version 3.7 (Release 2013a) September 2013 Online only Revised for Version 4.0 (Release 2013b) March 2014 Online only Revised for Version 4.0.1 (Release 2014a) October 2014 Online only Revised for Version 4.0.2 (Release 2014b) March 2015 Online only Revised for Version 4.1 (Release 2015a) Online only September 2015 Revised for Version 4.2 (Release 2015b) Online only Revised for Version 4.3 (Release 2016a) March 2016 September 2016 Online only Revised for Version 4.4 (Release 2016b) Online only Revised for Version 4.5 (Release 2017a) March 2017 September 2017 Online only Revised for Version 4.5.1 (Release 2017b) Online only Revised for Version 4.6 (Release 2018a) March 2018 September 2018 Online only Revised for Version 4.7 (Release 2018b) March 2019 Online only Revised for Version 4.8 (Release 2019a) Online only September 2019 Revised for Version 4.9 (Release 2019b) March 2020 Online only Revised for Version 4.10 (Release 2020a) Online only Revised for Version 5.0 (Release 2020b) September 2020 March 2021 Online only Revised for Version 5.1 (Release 2021a) Online only September 2021 Revised for Version 5.2 (Release 2021b) March 2022 Online only Revised for Version 5.3 (Release 2022a) September 2022 Online only Revised for Version 5.4 (Release 2022b)

Contents

Getting Sta	ırt
Mapping Toolbox Product Description	
Acknowledgments	
Create Your First World Map	
Getting More Help	
Understanding Map	Da
What Is a Map?	
•	
What Is Geospatial Data?	
Vector Geodata	
Raster Geodata	
Digital Elevation Data	
Combine Vector and Raster Geodata on the Same Map	
Combining Raster Data and Vector Data on the Same Map	
Create and Display Polygons	
Simple Polygon	
Polygons with Holes or Multiple Regions	2
Filled Region of Polygons Using Geographic Coordinates	2
Segments Versus Polygons	2
Create Geospatial Tables	2
Read Geospatial Table from File	2
Create Geospatial Table from Table	2
Create Geospatial Table from Arrays	2
•	

Geographic Data Structures	2-27
Shapefiles	2-27
The Contents of Geographic Data Structures	2-27
Examining a Geographic Data Structure	2-29
How to Construct Geographic Data Structures	2-30
Mapping Toolbox Version 1 Display Structures	2-3 4
Georeferenced Raster Data	2-35
Reference Objects	2-35
Referencing Matrices	2-35
Referencing Vectors	2-3 5
Construct a Global Data Grid	2-37
Geolocated Data Grids	2-39
Define Geolocated Data Grid	2-39
Define Geolocatea Data Grid	4-3 5
Geographic Interpretations of Geolocated Grids	2-4 3
Type 1: Values Associated with the Upper Left Grid Coordinate	2-4 3
Type 2: Values Centered Within Four Adjacent Coordinates	2-44
Ordering of Cells	2-45
Transform Regular to Geolocated Grids	2-45
Transforming Geolocated to Regular Grids	2-45
Transforming deviceated to negular Grids	2-10
Spatially Reference Imported Rasters	2-46
Differentiate Between Cells and Postings	2-46
Spatially Reference an Image	2-47
Spatially Reference an Elevation Grid	2-48
opularly reference an Elevation of a	- 10
Mosaic Spatially Referenced Raster Tiles	2-50
Mosaic Rasters of Cells	2-50
Mosaic Rasters of Postings	2-51
- 100a10 1ta00010 01 1 000111go	
Unprojecting a Digital Elevation Model (DEM)	2-5 4
Georeferencing an Image to an Orthotile Base Layer	2-65
Find Geospatial Data Online	2-77
Find Geospatial Vector Data	2-78
Find Geospatial Raster Data	2-79
Download Data	2-79
Use Web Map Service Data	2-80
•	
Functions that Read and Write Geospatial Data	2-81
Export Vector Geodata	2-8 3
Exporting Vector Data to KML	2-8 4
	n n-
Export KML Files for Viewing in Earth Browsers	2-95
Generate a Single Placemark Using kmlwritepoint	2-95
Generate Placemarks from Addresses	2-96
Export Point Geostructs to Placemarks	2-96

Select Snapenie Data to Read	2-99
Example 1: Predicate Function in Separate File	2-99
Example 2: Predicate as Function Handle	2-100
Example 3: Predicate as Anonymous Function	2-100
Example 4: Predicate (Anonymous Function) Defined Within Cell Array	2-101
Example 5: Parametrizing the Selector; Predicate as Nested Function .	2-101
Export Images and Raster Grids to GeoTIFF	2-103
Create, Process, and Export Digital Surface Model from Lidar Data	2-118
Converting Coastline Data (GSHHG) to Shapefile Format	2-12
Understanding Geospatial Geor	netr
The Shape of the Earth	
Ellipsoid Shape	
Geoid Shape	. 3-2
Reference Spheroids	
referenceSphere Objects	3-4
referenceEllipsoid Objects	3-6
World Geodetic System 1984	3-8
Ellipsoid Vectors	. 3-9
oblateSpheroid Objects	3-10
Work with Reference Spheroids	3-11
Map Projections	3-1 1
Curves and Areas	3-12
3-D Coordinate Transformations	3-12
Latitude and Longitude	3-13
Plot Latitude and Longitude	3-13
	2.4
Relationship Between Points on Sphere	3-15
Length and Distance Units	3-10
Choosing Units of Length	3-10
Converting Units of Length	3-10
Converting Cints of Longtin	5 1
Angle Representations and Angular Units	3-18
Degrees and Radians	3-18
Degree Representations	3-18
Latitude and Longitude Formats	3-19
Distances on the Sphere	3-2 2
Arc Length as an Angle in the distance and reckon Functions	3-22
Summary: Available Distance and Angle Conversion Functions	3-22
Const Charles	.
Great Circles	3-2 4

Rhumb Lines	3-25
Azimuth	
Elevation	3-28
Generate Vector Data for Points Along Great Circle or Rhumb Line	
Reckoning	3-31
Calculate Distance Between Two Points in Geographic Space	3-32
Generate Small Circles	3-33
Measure Area of Spherical Quadrangles	3-35
Plotting a 3-D Dome as a Mesh over a Globe	3-36
Comparison of 3-D Coordinate Systems Earth-Centered Earth-Fixed Coordinates Geodetic Coordinates East-North-Up Coordinates North-East-Down Coordinates Azimuth-Elevation-Range Coordinates Tips Vectors in 3-D Coordinate Systems Tips	3-42 3-43 3-44 3-44 3-45 3-46
Find Ellipsoidal Height from Orthometric Height Find Ellipsoidal Height from Orthometric and Geoid Height	
Creating and View	ving Maps
Introduction to Mapping Graphics	4-2
Continent, Country, Region, and State Maps Made Easy	4-3
Set Background Colors for Map Displays	4-4
Create Simple Maps Using worldmap	
	4-5

Map Limit Properties	4-12
Specify Map Projection Origin and Frame Limits Automatically	4-13
Create Cylindrical Projection Using Map Limit Properties	4-16
Create Conic Projection Using Map Limit Properties	4-18
Create Southern Hemisphere Conic Projection	4-19
Create North-Polar Azimuthal Projection	4-20
Create South-Polar Azimuthal Projection	4-22
Create Equatorial Azimuthal Projection	4-23
Create General Azimuthal Projection	4-24
Create Long Narrow Oblique Mercator Projection	4-25
3	
Switch Between Projections	4-27
Change Projection Updating Meridian and Parallel Labels	4-27
Change Projection Resetting Frame Limits	4-30
Change Projection Resetting Prame Limits	4-30
Demosite attion of Committee Objects	4.24
Reprojection of Graphics Objects	4-34
Auto-Reprojection of Mapped Objects and Its Limitations	4-34
Reprojectability of Maps Generated Using geoshow	4-35
Change Map Projections Using geoshow	4-37
Change Map Projection with Vector Data Using geoshow	4-37
Change Map Projection with Raster Data Using geoshow	4-38
The Map Frame	4-41
•	
Map and Frame Limits	4-43
Pup unu Tumo Limio	1 10
The Map Grid	4-44
Control Grid Spacing	4-44
	4-44 4-44
Layer Grids	
Limit Grid Lines	4-44
Label Grids	4-45
Summary of Polygon Display Functions	4-47
geoshow and mapshow	4-47
patchm, patchesm, fillm, and fill3m	4-47
geoplot	4-4 7
Display Vector Data as Points and Lines	4-49
Display Vector Data as Lines and Patches	4-52
Types of Data Grids and Raster Display Functions	4-58
	- 50
Fit Gridded Data to the Graticule	4-59
Fit Gridded Data to Fine and Coarse Graticules	4-59
The Gridden Data to Time and Coarse Grandines	4-39
Create 2 D Diorlana with Dagtor Data	4.60
Create 3-D Displays with Raster Data	4-63
Display Elevation Data in 3-D	4-63
Create Map Displays with Geographic Data	4-66
Create Maps with Data in Projected Coordinate Reference Systems	4-76
Pick Locations Interactively	4-85

Create Small Circle and Track Annotations on Maps Interactively	
Interactively Display Text Annotations on a Map	
Work with Objects by Name	
Making Three-Dimensional	N
Sources of Terrain Data Digital Terrain Elevation Data from NGA Digital Elevation Model Files from USGS	
Determine and Visualize Visibility Across Terrain	
Visualize Viewsheds and Coverage Maps Using Terrain	
Add Light Source to Terrain Map	
Surface Relief Shading	
Colored Surface Shaded Relief	
Relief Mapping with Light Objects	
Drape Data on Elevation Maps	
Drape Geoid Heights over Topography	
Combine Dissimilar Grids by Converting Regular Grid to Geolocated Da	ta
Access Basemaps and Terrain for Geographic Globe Use Installed Basemap Download Basemaps Add Custom Basemaps Access Terrain Specify Basemaps and Terrain	

Geographic Interpolation of Vectors		Customizing and Printing 1
Choropleth and Classification Maps Stem Maps Contour Maps Scatter Maps Create Choropleth Map from Table Data Create Classification Map from Table Data Create Choropleth Map of Population Density Scale Maps for Printing Create Common Plots over Basemap Images Change Projection of Basemap Image Use Basemaps in Offline Environments Temporary Internet Access No Internet Access Display Data over Basemaps When Internet Access Is Intermittent Manipulating Geospatial Geographic Interpolation of Vectors Vector Intersections	Inset Maps	
Choropleth and Classification Maps Stem Maps Contour Maps Scatter Maps Create Choropleth Map from Table Data Create Classification Map from Table Data Create Choropleth Map of Population Density Scale Maps for Printing Create Common Plots over Basemap Images Change Projection of Basemap Image Use Basemaps in Offline Environments Temporary Internet Access No Internet Access Display Data over Basemaps When Internet Access Is Intermittent Manipulating Geospatial Geographic Interpolation of Vectors Vector Intersections	Thematic Maps	
Contour Maps Scatter Maps Scatter Maps Create Choropleth Map from Table Data Create Classification Map from Table Data Create Choropleth Map of Population Density Scale Maps for Printing Create Common Plots over Basemap Images Change Projection of Basemap Image Use Basemaps in Offline Environments Temporary Internet Access No Internet Access Display Data over Basemaps When Internet Access Is Intermittent Manipulating Geospatial Geographic Interpolation of Vectors Vector Intersections		
Create Choropleth Map from Table Data Create Classification Map from Table Data Create Choropleth Map of Population Density Create Choropleth Map of Population Density Create Common Plots over Basemap Images Change Projection of Basemap Image Use Basemaps in Offline Environments Temporary Internet Access No Internet Access Display Data over Basemaps When Internet Access Is Intermittent Manipulating Geospatial Geographic Interpolation of Vectors Vector Intersections	-	
Create Choropleth Map from Table Data Create Classification Map from Table Data Create Choropleth Map of Population Density Create Common Plots over Basemap Images Change Projection of Basemap Image Use Basemaps in Offline Environments Temporary Internet Access No Internet Access Display Data over Basemaps When Internet Access Is Intermittent Manipulating Geospatial Geographic Interpolation of Vectors Vector Intersections	<u>-</u>	
Create Classification Map from Table Data Create Choropleth Map of Population Density Create Common Plots over Basemap Images Change Projection of Basemap Image Use Basemaps in Offline Environments Temporary Internet Access No Internet Access Display Data over Basemaps When Internet Access Is Intermittent Manipulating Geospatial Geographic Interpolation of Vectors Vector Intersections	Scatter Maps	
Create Choropleth Map of Population Density Scale Maps for Printing Create Common Plots over Basemap Images Change Projection of Basemap Image Use Basemaps in Offline Environments Temporary Internet Access No Internet Access Display Data over Basemaps When Internet Access Is Intermittent Manipulating Geospatial Geographic Interpolation of Vectors Vector Intersections	Create Choropleth Map from Table	Data
Create Common Plots over Basemap Images Change Projection of Basemap Image Use Basemaps in Offline Environments Temporary Internet Access No Internet Access Display Data over Basemaps When Internet Access Is Intermittent Manipulating Geospatial Geographic Interpolation of Vectors Vector Intersections	Create Classification Map from Tab	e Data
Create Common Plots over Basemap Images Change Projection of Basemap Image Use Basemaps in Offline Environments Temporary Internet Access No Internet Access Display Data over Basemaps When Internet Access Is Intermittent Manipulating Geospatial Geographic Interpolation of Vectors	Create Choropleth Map of Population	on Density
Change Projection of Basemap Image Use Basemaps in Offline Environments Temporary Internet Access No Internet Access Display Data over Basemaps When Internet Access Is Intermittent Manipulating Geospatial Geographic Interpolation of Vectors Wector Intersections	Scale Maps for Printing	
Use Basemaps in Offline Environments Temporary Internet Access No Internet Access Display Data over Basemaps When Internet Access Is Intermittent Manipulating Geospatial Geographic Interpolation of Vectors Vector Intersections	Create Common Plots over Basema	Images
Temporary Internet Access No Internet Access Display Data over Basemaps When Internet Access Is Intermittent Manipulating Geospatial Geographic Interpolation of Vectors Vector Intersections	Change Projection of Basemap Ima	ge
No Internet Access Display Data over Basemaps When Internet Access Is Intermittent Manipulating Geospatial Geographic Interpolation of Vectors Vector Intersections	Use Basemaps in Offline Environme	nts
Display Data over Basemaps When Internet Access Is Intermittent Manipulating Geospatial Geographic Interpolation of Vectors Vector Intersections		
Manipulating Geospatial Geographic Interpolation of Vectors	No Internet Access	
Geographic Interpolation of Vectors	Display Data over Basemaps When	Internet Access Is Intermittent
Vector Intersections		Manipulating Geospatial
Polygon Set Logic	Geographic Interpolation of Vectors	
	-	
Polygon Buffer Zones	Vector Intersections	
Generate Buffer Internal to Polygon	Vector Intersections	
Simplify Vector Coordinate Data	Vector Intersections Polygon Set Logic Polygon Buffer Zones	
Simplify Vector Coordinate Data	Vector Intersections	

Visualize UAV Flight Path on 2-D and 3-D Maps

5-81

Data Grids as Logical Variables	7-16
<u>-</u>	

Using Map Projections and Coordinate Systems

Map Projections and Distortions8-3Use Inverse Projection to Recover Geographic Coordinates8-3Projection Distortions8-3
Quantitative Properties of Map Projections 8-4
The Three Main Families of Map Projections8-1Unwrapping the Sphere to a Plane8-1Cylindrical Projections8-1Conic Projections8-1Azimuthal Projections8-1
Projection Aspect8-5The Orientation Vector8-5Control the Map Projection Aspect with an Orientation Vector8-1
Projection Parameters8-10Projection Characteristics Maps Can Have8-10
Visualize Spatial Error Using Tissot Indicatrices 8-22 Visualize Projection Distortions Using Tissot Indicatrices 8-22
Quantify Map Distortions at Point Locations 8-20 Use distortcalc to Determine Map Projection Geometric Distortions 8-20
Rotational Transformations on the Globe Reorient Vector Data with rotatem
Create a UTM Map
Set UTM Parameters Interactively 8-38
Work in UTM Without a Displayed Map 8-4
Use the Transverse Aspect to Map Across UTM Zones 8-43
Summary and Guide to Projections8-48Cylindrical Projections8-48Pseudocylindrical Projections8-48Conic Projections8-52Pseudoconic Projections8-53Polyconic Projections8-54Azimuthal Projections8-54Pseudoazimuthal Projections8-55Modified Azimuthal Projections8-57

Project and Display Raster Data	8- 8- 8-
Creating Web Map Service I	Мa
Basic WMS Terminology	,
Basic Workflow for Creating WMS Maps	!
Add Legend to WMS Map	
Read WMS Maps Using Different Coordinate Reference Systems	9
Modify Your Map Request	9
Set Map Request Geographic Limits and Time	9
Manually Edit Web Map Request URL	9
Overlay Multiple Layers	9
Create Composite Map of Multiple Layers from One Server	9
Combine Layers from One Server with Data from Other Sources	9
Drape Orthoimagery Over DEM	9
Animate Data Layers	9
Create Movie of Terra/MODIS Maps	9
Create Animated GIF of WMS Maps	9
Create Animation of Time-Lapse Radar Observations	9
Display Animation of Radar Images over GOES Backdrop	9
Read Quantitative Data from WMS Server	9
Read and Display Terrain Elevation Data	9
Merge Elevation Data with Rasterized Vector Data	9
Drape Basemap Imagery onto Elevation Data	9
Tips	g
Explore Layers on Same Server	9
Write WMS Layers to KML File	9
Search for Layers Outside the WMS Database	9
Create WMS Maps When Internet Access Is Intermittent	9
Troubleshoot WMS Servers	9
Connection Errors	9
Intermittent Internet Access	9
Geographic Limits in Descending Order or Out of Bounds	9

Transform Coordinates to a Different Projected CRS 8-58

	Non-EPSG:4326 Coordinate Reference Systems Map Not Returned Unsupported WMS Version	9-55 9-56 9-57
	Other Unrecoverable Server Errors	9-57
	Introduction to Web Map Display	9-58 9-60
	Basic Workflow for Displaying Web Maps	9-61 9-61
	Display a Web Map	9-62
	Select a Base Layer Map	9-63
	Specify a Custom Base Layer	9-65
	Specify a WMS Layer as a Base Layer	9-67
	Add an Overlay Layer to the Map	9-69
	Add Line, Polygon, and Marker Overlay Layers to Web Maps	9-71
	Remove Overlay Layers on a Web Map	9-77
	Navigate a Web Map	9-81
	Close a Web Map	9-83
	Annotate a Web Map with Measurement Information	9-84
	Compositing and Animating Web Map Service (WMS) Meteorological Layers	9-88
	Troubleshoot Common Problems with Web Maps Why Does My Web Map Contain Empty Tiles? Why Does My Web Map Lose Detail When I Zoom In?	9-103 9-103 9-103
10 [Mapping Applica	tions
	Geographic Statistics for Point Locations on a Sphere	10-2 10-2 10-3
	Equal-Areas in Geographic Statistics Geographic Histograms	10-6 10-6 10-7
	Navigation	10-9 10-9

10-9
10-11 10-11 10-14 10-16
10-20
10-23
10-26
10-30
10-32

Map Projections — Alphabetical List

11

Getting Started

This chapter provides step-by-step examples of basic Mapping Toolbox capabilities and guides you toward examples and documentation that can help answer your questions. For an alphabetical list of functions click on MATLAB Functions link at bottom of main Mapping Toolbox page.

- "Mapping Toolbox Product Description" on page 1-2
- "Acknowledgments" on page 1-3
- "Create Your First World Map" on page 1-4
- "Getting More Help" on page 1-9

Mapping Toolbox Product Description

Analyze and visualize geographic information

Mapping Toolbox provides algorithms and functions for transforming geographic data and creating map displays. You can visualize your data in a geographic context, build map displays from more than 60 map projections, and transform data from a variety of sources into a consistent geographic coordinate system.

Mapping Toolbox supports a complete workflow for managing geographic data. You can import vector and raster data from a wide range of file formats and web map servers. The toolbox lets you process and customize data using trimming, interpolation, resampling, coordinate transformations, and other techniques. Data can be combined with base map layers from multiple sources in a single map display. You can export data in file formats such as shapefile, GeoTIFF, and KML.

Acknowledgments

This software was originally developed and maintained through Version 1.3 by Systems Planning and Analysis, Inc. (SPA), of Alexandria, Virginia.


Except where noted, the information contained in example and sample data files (found in <code>matlabroot/examples/map/data</code> and <code>matlabroot/toolbox/map/mapdata</code>) is derived from publicly available digital data sets. These data files are provided as a convenience to Mapping Toolbox users. MathWorks® makes no claims that any of this data is free of defects or errors, or that the representations of geographic features or names are up to date or authoritative.

Create Your First World Map

This example shows how to use the Mapping Toolbox $^{\text{\tiny{TM}}}$ to create a world map. Geospatial data can be voluminous, complex, and difficult to process. Mapping Toolbox functions handle many of the details of loading and displaying geospatial data, and use built-in data structures that facilitate data storage. *Spatial data* refers to data describing location, shape, and spatial relationships. *Geospatial data* is spatial data that is in some way georeferenced, or tied to specific locations on, under, or above the surface of a planet.

Create an empty axesm-based map (previously referred to as map axes), ready to hold the data of your choice. The function worldmap automatically selects a reasonable choice for your map projection and coordinate limits. To display a world map, the function chose a Robinson projection centered on the prime meridian and the equator (0° latitude, 0° longitude).

worldmap world



Import low-resolution world coastline data. The coastline data is a set of discrete vertices that, when connected in the order given, approximate the coastlines of continents, major islands, and inland seas. The vertex latitudes and longitudes are stored as vectors in a MAT-file. Load the MAT-file and view the variables in the workspace.

load coastlines whos

Name Size Bytes Class Attributes

```
coastlat 9865x1 78920 double coastlon 9865x1 78920 double
```


Determine how many separate elements are in the coastline data vectors. Even though there is only one vector of latitudes, coastlat, and one vector of longitudes, coastlon, each of these vectors contain many distinct polygons, forming the worlds coastlines. These vectors use NaN separators and NaN terminators to divide each vector into multiple parts.

```
[latcells, loncells] = polysplit(coastlat, coastlon);
numel(latcells)
```


ans = 241


Plot the coastline data on the map using the plotm function. plotm is the geographic equivalent of the MATLAB® plot function. It accepts coordinates in latitude and longitude, transforms them to x and y via a specified map projection, and displays them. In this example, worldmap uses the Robinson projection.

plotm(coastlat, coastlon)



Create a new map for plotting data over Europe. This time, specify a return argument for the worldmap function to get a handle to the axesm-based map. An axesm-based map is a standard MATLAB axes with different default settings for some properties and a structure for storing projection parameters and other data. In addition to the graphics properties common to any MATLAB axes object, an axesm-based map contains additional properties covering map projection type, projection parameters, map limits, etc. The getm and setm functions and others allow you to access and modify these properties.






Determine which map projection worldmap is using.

```
getm(h,'MapProjection')
ans =
'eqdconic'
```


Add data to the map of Europe by using the geoshow function to import and display several sample shapefiles. Note how the geoshow function can plot data directly from files onto a map without first importing it into the workspace. To change the color of the marker, use the MarkerEdgeColor property and, for some markers, the MarkerFaceColor property.

```
geoshow('landareas.shp', 'FaceColor', [0.15 0.5 0.15])
geoshow('worldlakes.shp', 'FaceColor', 'cyan')
geoshow('worldrivers.shp', 'Color', 'blue')
geoshow('worldcities.shp', 'Marker', '.',...
                                                                       'MarkerEdgeColor', 'magenta')
```



Place a label on the map to identify the Mediterranean Sea.

```
labelLat = 35;
labelLon = 14;
textm(labelLat, labelLon, 'Mediterranean Sea')
```



Getting More Help

Ways to Get Mapping Toolbox Help

Help is available for individual commands and classes of Mapping Toolbox commands:

- help functionname for help on a specific function, often including examples
- doc *functionname* to read a function's reference page in the Help browser, including examples and illustrations
- help map for a list of functions by category
- mapdemos for a list of Mapping Toolbox examples
- maps to see a list of all Mapping Toolbox map projections by class, name, and ID
- maplist to return a structure describing all Mapping Toolbox map projections
- projlist to list map projections supported by projfwd and projinv

Understanding Map Data

- "What Is a Map?" on page 2-2
- "What Is Geospatial Data?" on page 2-3
- "Vector Geodata" on page 2-4
- "Raster Geodata" on page 2-5
- "Combine Vector and Raster Geodata on the Same Map" on page 2-6
- "Create and Display Polygons" on page 2-8
- "Segments Versus Polygons" on page 2-16
- "Create Geospatial Tables" on page 2-18
- "Combine Vector Data Using Table Joins" on page 2-23
- "Geographic Data Structures" on page 2-27
- "Georeferenced Raster Data" on page 2-35
- "Construct a Global Data Grid" on page 2-37
- "Geolocated Data Grids" on page 2-39
- "Geographic Interpretations of Geolocated Grids" on page 2-43
- "Spatially Reference Imported Rasters" on page 2-46
- "Mosaic Spatially Referenced Raster Tiles" on page 2-50
- "Unprojecting a Digital Elevation Model (DEM)" on page 2-54
- "Georeferencing an Image to an Orthotile Base Layer" on page 2-65
- "Find Geospatial Data Online" on page 2-77
- "Find Geospatial Vector Data" on page 2-78
- "Find Geospatial Raster Data" on page 2-79
- "Functions that Read and Write Geospatial Data" on page 2-81
- "Export Vector Geodata" on page 2-83
- "Exporting Vector Data to KML" on page 2-84
- "Export KML Files for Viewing in Earth Browsers" on page 2-95
- "Select Shapefile Data to Read" on page 2-99
- "Export Images and Raster Grids to GeoTIFF" on page 2-103
- "Create, Process, and Export Digital Surface Model from Lidar Data" on page 2-118
- "Converting Coastline Data (GSHHG) to Shapefile Format" on page 2-127

What Is a Map?

Mapping Toolbox software manipulates electronic representations of geographic data. It lets you import, create, use, and present geographic data in various forms and to various ends. In the digital network era, it is easy to think of geospatial data as maps and maps as data, but you should take care to note the differences between these concepts.

The simplest (although perhaps not the most general) definition of a *map* is a representation of geographic data. Most people today generally think of maps as two-dimensional; to the ancient Egyptians, however, maps first took the form of lists of place names in the order they would be encountered when following a given road. Today such a list would be considered as *map data* rather than as a map. When most people hear the word "map" they tend to visualize two-dimensional renditions such as printed road, political, and topographic maps, but even classroom globes and computer graphic flight simulation scenes are maps under this definition.

In this toolbox, map data is any variable or set of variables representing a set of geographic locations, properties of a region, or features on a planet's surface, regardless of how large or complex the data is, or how it is formatted. Such data can be rendered as maps in a variety of ways using the functions and user interfaces provided.

What Is Geospatial Data?

Geospatial data comes in many forms and formats, and its structure is more complicated than tabular or even nongeographic geometric data. It is, in fact, a subset of spatial data, which is simply data that indicates where things are within a given *coordinate system*. Mileposts on a highway, an engineering drawing of an automobile part, and a rendering of a building elevation all have coordinate systems, and can be represented as spatial data when properly quantified (digitized). Such coordinate systems, however, are local and not explicitly tied or oriented to the Earth's surface; thus, most digital representations of mileposts, machine parts, and buildings do not qualify as geospatial data (also called *geodata*).

What sets geospatial data apart from other spatial data is that it is absolutely or relatively positioned on a planet, or *georeferenced*. That is, it has a *terrestrial coordinate system* that can be shared by other geospatial data. There are many ways to define a terrestrial coordinate system and also to transform it to any number of local coordinate systems, for example, to create a map projection. However, most are based on a framework that represents a planet as a sphere or spheroid that spins on a north-south axis, and which is girded by an *equator* (an imaginary plane midway between the poles and perpendicular to the rotational axis).

Geodata is coded for computer storage and applications in two principal ways: *vector* and *raster* representations. It has been said that "raster is faster but vector is corrector." There is truth to this, but the situation is more complex. For more information, see "Vector Geodata" on page 2-4 and "Raster Geodata" on page 2-5.

Vector Geodata

Vector data (in the computer graphics sense rather than the physics sense) can represent a map. Such vectors take the form of sequences of latitude-longitude or projected coordinate pairs representing a point set, a linear map feature, or an areal map feature. For example, points delineating the boundary of the United States, the interstate highway system, the centers of major U.S. cities, or even all three sets taken together, can be used to make a map. In such representations, the geographic data is in *vector* format and displays of it are referred to as *vector maps*. Such data consists of lists of specific coordinate locations (which, if describing linear or areal features, are normally points of inflection where line direction changes), along with some indication of whether each is connected to the points adjacent to it in the list.

In the Mapping Toolbox environment, vector data consists of sequentially ordered pairs of geographic (latitude, longitude) or projected (x,y) coordinate pairs (also called tuples). Successive pairs are assumed to be connected in sequence; breaks in connectivity must be delineated by the creation of separate vector variables or by inserting separators (usually NaNs) into the sets at each breakpoint. For vector map data, the connectivity (topological structure) of the data is often only a concern during display, but it also affects the computation of statistics such as length and area.

You can represent vector data by using geospatial tables or data structures. For more information about geospatial tables, see "Create Geospatial Tables" on page 2-18. For more information about data structures, see "Geographic Data Structures" on page 2-27.

Raster Geodata

You can map data represented as a *matrix* (a 2-D MATLAB® array) in which each row-and-column element corresponds to a rectangular patch of a specific geographic area, with implied topological connectivity to adjacent patches. This is commonly referred to as *raster data*. *Raster* is actually a hardware term meaning a systematic scan of an image that encodes it into a regular grid of pixel values arrayed in rows and columns.

When data in raster format represents the surface of a planet, it is called a *data grid*, and the data is stored as an array or matrix. The toolbox leverages the power of MATLAB matrix manipulation in handling this type of map data. This documentation uses the terms *raster data* and *data grid* interchangeably to talk about geodata stored in two-dimensional array form.

A raster can encode either an average value across a cell or a value sampled (posted) at the center of that cell. While geolocated data grids explicitly indicate which type of values are present (see "Geolocated Data Grids" on page 2-39), external metadata/user knowledge is required to be able to specify whether a regular data grid encodes averages or samples of values.

Digital Elevation Data

When raster geodata consists of surface elevations, the map can also be referred to as a *digital elevation model/matrix* (DEM), and its display is a *topographical map*. The DEM is one of the most common forms of *digital terrain model* (DTM), which can also be represented as contour lines, triangulated elevation points, quadtrees, octree, or otherwise.

The topo60c MAT-file, which contains global terrain data, is an example of a DEM. In this 180-by-360 matrix, each row represents one degree of latitude, and each column represents one degree of longitude. Each element of this matrix is the average elevation, in meters, for the one-degree-by-one-degree region of the Earth to which its row and column correspond.

Remotely Sensed Image Data

Raster geodata also encompasses georeferenced imagery. Like data grids, images are organized into rows and columns. There are subtle distinctions, however, which are important in certain contexts. One distinction is that an image may contain RGB or multispectral channels in a single array, so that it has a third (color or spectral) dimension. In this case a 3-D array is used rather than a 2-D (matrix) array. Another distinction is that while data grids are stored as class double in the toolbox, images may use a range of MATLAB storage classes, with the most common being uint8, uint16, double, and logical. Finally, for grayscale and RGB images of class double, the values of individual array elements are constrained to the interval [0 1].

In terms of georeferencing—converting between column/row subscripts and 2-D map or geographic coordinates—images and data grids behave the same way (which is why both are considered to be a form of raster geodata). However, when performing operations that process the values raster elements themselves, including most display functions, it is important to be aware of whether you are working with an image or a data grid, and for images, how spectral data is encoded.

Combine Vector and Raster Geodata on the Same Map

Vector map variables and data grid variables are often used or displayed together. For example, continental coastlines in vector form might be displayed with a grid of temperature data to make the latter more useful. When several map variables are used together, regardless of type, they can be referred to as a single map. To do this, of course, the different data sets must use the same coordinate system (i.e., geographic coordinates on the same ellipsoid or an identical map projection).

Combining Raster Data and Vector Data on the Same Map


This example shows how to combine raster data and vector data on the same axesm-based map using the geoshow function.

First, load elevation raster data and a geographic cells reference object. Get the coordinates of coastlines as vectors.

```
load topo60c
load coastlines
```


Create an axesm-based map using a Robinson projection. Then, display the raster and apply a colormap appropriate for elevation data.

```
axesm robinson
geoshow(topo60c,topo60cR,'DisplayType','texturemap')
demcmap(topo60c)
```




Display the vectors in red on top of the elevation map.

geoshow(coastlat,coastlon,'Color','r')



Create and Display Polygons

Polygons represent geographic objects that cover area, such as continents, islands, and lakes. They may contain holes or multiple regions. Create a polygon by listing vertices that define its boundaries without intersecting. The order of the vertices determines what parts of the polygon are filled. List external boundaries clockwise and internal boundaries counterclockwise, such that the inside of the polygon is always to the right of the boundary.



Simple Polygon


Display a simple polygon with one region and no holes. First, list its vertices in a clockwise order. Close the polygon by repeating the first vertex at the end of the list.

```
x1 = [0 \ 3 \ 4 \ 1 \ 0];

y1 = [0 \ 1 \ 3 \ 2 \ 0];
```

Display the vertices as a polygon using the mapshow function by specifying 'DisplayType' as 'polygon'.

```
mapshow(x1,y1,'DisplayType','polygon')
```



Polygons with Holes or Multiple Regions

Define polygons with multiple regions or holes by separating the boundaries with NaN values. List the vertices of external boundaries in a clockwise order and the vertices of internal boundaries in a counterclockwise order.

```
x2 = [0 \ 1 \ 8 \ 6 \ 0 \ NaN \ 1 \ 4 \ 2 \ 1 \ NaN \ 5 \ 6 \ 7 \ 3 \ 5];


y2 = [0 \ 6 \ 8 \ 2 \ 0 \ NaN \ 1 \ 3 \ 5 \ 1 \ NaN \ 3 \ 5 \ 7 \ 6 \ 3];
```

These vectors define a polygon with one external boundary and two internal boundaries. The boundaries are separated using NaN values. Verify the vertex order of the boundaries using the <code>ispolycw</code> function. The <code>ispolycw</code> function returns 1 when the vertices are in a clockwise order.

```
ispolycw(x2,y2)
ans = 1x3 logical array
1 0 0
```

Display the polygon. The internal boundaries create holes within the polygon.

```
figure
mapshow(x2,y2,'DisplayType','polygon')
```




Now, list the vertices for a polygon with two nonintersecting regions. One of the regions has a hole. Verify the vertex order of the boundaries using ispolycw.

```
x3 = [0 1 5 6 0 NaN 1 5 4 2 1 NaN 7 6 8 8 7];
y3 = [0 6 7 2 0 NaN 1 3 6 5 1 NaN 4 7 8 7 4];
ispolycw(x3,y3)
ans = 1x3 logical array
```

Display the polygon. The external boundaries create two nonintersecting regions and the internal boundary creates a hole.

```
figure
mapshow(x3,y3,'DisplayType','polygon')
```



Polygons Using Geographic Coordinates

In general, you can use geographic coordinates when you define polygons over small regions and call functions such as <code>ispolycw</code>. This is true except in cases where the polygon wraps a pole or crosses the Antimeridian.

For example, display the state of Michigan on a map using polygons with geographic coordinates. First, read the vertices of the state boundaries.


```
states = shaperead('usastatehi.shp','UseGeoCoords',true);
michigan = states(22);
lat = michigan.Lat;
lon = michigan.Lon;
```

Count the boundaries and verify their vertex order. To use <code>ispolycw</code> with geographic coordinates, list the longitude vector as the first argument and the latitude vector as the second argument. The 1-by-6 output array means there are six boundaries. Each element of the array is 1, which means that each boundary is the exterior boundary of its own region.

```
ispolycw(lon,lat)
ans = 1x6 logical array
     1     1     1     1     1     1
```


Display the polygon on a map using the geoshow function, specifying 'DisplayType' as 'polygon'.

```
usamap 'Michigan'
geoshow(lat,lon,'DisplayType','polygon')
```




Clip the polygon to the latitude and longitude limits of Isle Royale National Park using the maptrimp function. Display the clipped polygon on a new map.

```
latlim = [47.8 48.2];
lonlim = [-89.3 -88.4];
[latT,lonT] = maptrimp(lat,lon,latlim,lonlim);
figure
usamap(latlim,lonlim)
geoshow(latT,lonT,'DisplayType','polygon')
```



Filled Region of Polygons Using Geographic Coordinates


When you display a polygon on the Earth, the boundary divides the Earth into two regions. Both of these regions have finite area, so either could be the inside region of the polygon.



As a result, when you project the vertices of a polygon onto a map using the <code>geoshow</code> function, the filled region may be different than you expect. Change which region is filled by reversing the order of the vertices.


For example, display a small polygon on a world map.

```
lat2 = [0 10 40 30 0];
lon2 = [0 20 30 10 0];
figure
worldmap('world')
geoshow(lat2,lon2,'DisplayType','polygon')
```



The outside region of the polygon is filled. Reverse the order of the vertices by applying the flip function to the coordinate vectors. Then, display the polygon again.

```
lat2f = flip(lat2);
lon2f = flip(lon2);
figure
worldmap('world')
geoshow(lat2f,lon2f,'DisplayType','polygon')
```



The inside region of the polygon is filled instead.

See Also

Functions

ispolycw|worldmap|geoshow|mapshow

Objects


polyshape | mappolyshape | geopolyshape

Segments Versus Polygons

Geographic objects represented by vector data might or might not be formatted as polygons. Imagine two variables, latcoast and loncoast, that correspond to a sequence of points that caricature the coast of the island of Great Britain. If this data returns to its starting point, then a polygon describing Great Britain exists. This data might be plotted as a patch or as a line, and it might be logically employed in calculations as either.

Now suppose that you want to represent the Anglo-Scottish border, proceeding from the west coast at Solway Firth to the east coast at Berwick-upon-Tweed. This data can only be properly defined as a line, defined by two or more points, which you can represent with two more variables, latborder and lonborder. When plotted together, the two pairs of variables can form a map. The patch of Great Britain plus the line showing the Scottish border might look like two patches or regions, but there is no object that represents England and no object that represents Scotland, either in the workspace or on the map.

In order to represent both regions properly, the Great Britain polygon needs to be split at the two points where the border meets it, and a copy of latborder and lonborder concatenated to both lines (placing one in reverse order). The resulting two polygons can be represented separately (e.g., in four variables named latengland, lonengland, latscotland, and lonscotland) or in two variables that define two polygons each, delineated by NaNs (e.g., latuk, lonuk).



The distinction between line and polygon data might not appear to be important, but it can make a difference when you are performing geographic analysis and thematic mapping. For example, polygon data can be treated as line data and displayed with functions such as linem, but line data cannot be handled as polygons unless it is restructured to make all objects close on themselves.

See Also

geoshow | polymerge

More About

• "Create and Display Polygons" on page 2-8

Create Geospatial Tables

Vector data uses points, lines, polygons, and their nonspatial attributes to describe real-world events, locations and objects. For example, you can use a point and timestamp attribute to represent a tsunami event, a line and name attribute to represent a river location, and a polygon and age attribute to represent a building.

You can represent vector data by using geospatial tables. A geospatial table is a table or timetable object that contains a Shape variable and attribute variables.

• The Shape variable contains 2-D information about point, line, and polygon shapes. The Shape variable can contain combinations of shape types, but all the shapes must have the same coordinate reference system (CRS). The Shape variable must be the first variable of the table.

Represent shapes with coordinates in geographic CRSs by using geopointshape, geolineshape, and geopolyshape objects. The Geographic CRS property of each object contains the CRS as a geocrs object.

Represent shapes with coordinates in projected CRSs by using mappointshape, maplineshape, and mappolyshape objects. The ProjectedCRS property of each object contains the CRS as a projers object.

• The attribute variables contain data such as names, classifications, and measurements.

For example, you can import the shapefile <code>concord_roads.shp</code>, which represents a road network in Concord, MA, as a geospatial table. Each row of the table contains a <code>maplineshape</code> object with information about the line shape and several attributes with information such as the street name, road class, and road length.

There are multiple ways to create geospatial tables. You can:

- Read a geospatial table from a vector data file by using the readgeotable function.
- Read a table or timetable from a file containing pointwise data or well-known text (WKT) string representations of geometry by using the readtable or readtimetable function, and then convert the table to a geospatial table by using the table2geotable function.
- Create a geospatial table by using the table or timetable function. For more information about creating tables, see "Create Tables and Assign Data to Them". For more information about creating timetables, see "Create Timetables".

These examples show how to create geospatial tables using each of the listed processes.

Read Geospatial Table from File

Read a shapefile containing a network of road segments in Concord, MA as a geospatial table by using the readgeotable function.

```
GT = readgeotable("concord_roads.shp");
```

View the first eight rows of the geospatial table. The **Shape** variable contains information about the shapes. For this example, all the shapes are lines. The other variables contain attribute data.

head(GT)

Shape	STREETNAME	RT_NUMBER	CLASS	ADMIN_TYPE	LENGTH
maplineshape	11 11	нн	6	0	67.264
maplineshape	"WRIGHT FARM"	11 11	5	0	72.178
maplineshape	"WRIGHT FARM"	11 11	5	0	43.965
maplineshape	"WRIGHT FARM"	11.11	5	0	109.65
maplineshape	"WRIGHT FARM"	11.11	5	0	18.019
maplineshape	II II	11.11	6	0	58.444
maplineshape	"WRIGHT FARM"	11 11	5	0	16.925
maplineshape	н н	11.11	6	0	55.633

View the projected CRS for the line shapes. All shapes in a geospatial table must have the same CRS.


GT.Shape.ProjectedCRS

View information about the line shape in the first row of the table.

GT.Shape(1)

Display the roads.

mapshow(GT)



Create Geospatial Table from Table

Read data about tsunami events as a table by using the readtable function. The coordinates of the tsunami source locations are in the Latitude and Longitude table variables.

```
T = readtable("tsunamis.xlsx");
```

Convert the table to a geospatial table by using the table2geotable function. The function detects the Latitude and Longitude variables and uses them to create the Shape variable of the table.

```
GT = table2geotable(T);
```

View the Shape variable of the geospatial table. The tsunami source locations are points in a geographic coordinate system.

GT.Shape


```
ans =
   162×1 geopointshape array with properties:

        NumPoints: [162×1 double]
        Latitude: [162×1 double]
        Longitude: [162×1 double]
        Geometry: "point"
   CoordinateSystemType: "geographic"
```

GeographicCRS: []

Plot the source locations on a web map. Display the attributes for a shape by selecting a marker.

wmmarker(GT)



Create Geospatial Table from Arrays

Create a geospatial table containing the locations and names of cities.

Create an array of <code>geopointshape</code> objects from column vectors of latitude and longitude coordinates. Specify the geographic CRS as the World Geodetic System of 1984, which has the EPSG code 4326.

```
Geometry: "point"
CoordinateSystemType: "geographic"
GeographicCRS: [1x1 geocrs]
```

Specify the names of the cities as a column vector.

```
names = ["Tokyo" "Rio de Janeiro" "London" "Beijing" "Athens"]';
```

Create the geospatial table. The Shape variable contains the geopointshape objects and the Name variable contains the names.

```
GT = table(shape,names,VariableNames=["Shape" "Name"])
```

```
GT=5×2 table
Shape
Name

(35.7082°N, 139.6401°E)
(22.8842°S, 43.3882°W)
(51.5074°N, 0.1278°W)
(39.9042°N, 116.4074°E)
(37.9838°N, 23.7275°E)

"Name

"Tokyo"
"Rio de Janeiro"
"London"
"Beijing"
"Athens"
```

Verify that the table is a geospatial table.

```
isgeotable(GT)
```

```
ans = logical
1
```

Tips

Some functions that accept geospatial tables as input require the geospatial table to contain shapes of a specific type. For example, the kmlwrite function only accepts geospatial tables that contain geographic point, line, or polygon shapes.

See Also

Functions

readgeotable | readtable | table2geotable | struct2geotable | isgeotable

Objects

table | timetable

Combine Vector Data Using Table Joins

To link vector data from one file to vector data with shared attributes from other files, import the files as tables and use a table join. A *table join* combines two tables by row according to key variables such as state names, alphanumeric IDs, or Federal Information Processing System (FIPS) codes.

This example shows you how to read data from two different files into separate tables, join the tables, create a choropleth map from the joined table, and export the joined table into a shapefile.

Read Data into Tables

Read a comma-separated text file into a table. The file contains farmland statistics for each US state and the District of Columbia, based on the National Agricultural Statistics Service (NASS) Farms and Land in Farms 2019 Summary. For more information about the statistics, see [1] on page 2-26. Display the first row of the table.

To create a map from the table, you also need spatial information. Read a shapefile containing polygon shapes for each of the US states and the District of Columbia into a geospatial table. A *geospatial table* has a Shape variable containing shape information for each row. Display the first row of the geospatial table.

The Shape variable of the table contains geopolyshape objects, which are polygons in geographic coordinates. Display the properties of the geopolyshape object in the first row.

```
states.Shape(1)
ans =
   geopolyshape with properties:

        NumRegions: 1
        NumHoles: 0
        Geometry: "polygon"
        CoordinateSystemType: "geographic"
        GeographicCRS: [1×1 geocrs]
```

Join Tables

Join the tables, using the state name variables Name and StateName as the key variables. Display the first row of the joined table.

```
statesFarms = outerjoin(states, farms, LeftKey="Name", RightKey="StateName");
statesFarms(1,:)
```

ans=1×9 table Shape	Name	LabelLat	LabelLon	PopDens2000	StateName	NumberOfFar
geopolyshape	"Alabama"	32.283	-86.921	87.6	"Alabama"	38800

The outerjoin function creates a table that includes rows where the key variables from one input table have no matches in the other input table. As a result, the output table can have more rows than either of the input tables. To create a table that includes the rows from one input table and appends rows where the key variables match values in the key variables of the other input table, use the join function instead. To create a table that includes only the rows where the key variables from one input table have matching values in the other input table, use the innerjoin function instead.

Inspect Joined Table

Mismatches in key variables can cause unexpected results in the joined table. Inspect the joined table by displaying the number of rows.

```
height(statesFarms)
ans = 52
```

Each input table contains 51 rows, but the joined table contains 52 rows. Because the state names are the key variables, this result indicates a mismatch in the names.

The table of farmland statistics identifies the District of Columbia as Washington DC, which does not match the corresponding row of the table of polygon shapes. Change the name in the table of farmland statistics so that it matches the name in the table of polygon shapes.

```
dcRow = farms.StateName == "Washington DC";
farms.StateName(dcRow) = "District of Columbia";
```

Join the tables again and display the number of rows in the joined table.

```
statesFarms = outerjoin(states, farms, LeftKey="Name", RightKey="StateName");
height(statesFarms)
```

ans = 51

The number of rows in the output table matches the number of rows in the input table.

Sort the joined table by average farm size and display the top eight rows.

```
topkrows(statesFarms, 8, "AverageFarmSize")
```

```
ans=8×9 table
Shape Name LabelLat LabelLon PopDens2000 StateName
```

geopolyshape	"Wyoming"	43.033	-107.56	5.1	"Wyoming"
geopolyshape	"Montana"	46.867	-110.58	6.2	"Montana"
geopolyshape	"Nevada"	39.177	-116.4	18.2	"Nevada"
geopolyshape	"New Mexico"	34.291	-106.18	15	"New Mexico"
geopolyshape	"North Dakota"	47.469	-99.5	9.3	"North Dakota"
geopolyshape	"South Dakota"	44.272	-99.679	9.9	"South Dakota"
geopolyshape	"Arizona"	34.345	-112.07	45.2	"Arizona"
geopolyshape	"Nebraska"	41.504	-99.435	22.3	"Nebraska"


Create Map

Create a choropleth map of average farm size for the conterminous US.

```
figure
rows = statesFarms.Name ~= "Hawaii" & statesFarms.Name ~= "Alaska";
geoplot(statesFarms(rows,:),ColorVariable="AverageFarmSize")
geobasemap topographic
```

Add a title and colorbar.

```
title("Average Farm Size Per US State in 2019")
cb = colorbar;
cb.Label.String = "Size in Acres";
```



AAFC, NRCan

90°W

Longitude

Esri, HERE, Garmin, FAO, NOAA, EPA,

75°W

Average Farm Size Per US State in 2019

Export Table as Shapefile

500 mi

120°W

Export the joined table as a new shapefile.

105°W

shapewrite(statesFarms, "usastatelo_farmland.shp")

References

[1] National Agricultural Statistics Service. "Number of Farms, Land in Farms, and Average Farm Size — States and United States: 2018–2019." *In Farms and Land in Farms 2019 Summary*, 6. USDA, February 2020. https://www.nass.usda.gov/Publications/Todays_Reports/reports/fnlo0220.pdf.

See Also

Functions

readtable | readgeotable

Objects

geopolyshape

Related Examples

"Create Geospatial Tables" on page 2-18

Geographic Data Structures

Mapping Toolbox software provides an easy means of displaying, extracting, and manipulating collections of vector map features organized in *geographic data structures*.

A geographic data structure is a MATLAB structure array that has one element per geographic feature. Each feature is represented by coordinates and attributes. A geographic data structure that holds geographic coordinates (latitude and longitude) is called a geostruct, and one that holds map coordinates (projected x and y) is called a mapstruct. Geographic data structures hold only vector features and cannot be used to hold raster data (regular or geolocated data grids or images).

Alternatively, you can represent vector data by using geospatial tables. Geospatial tables are table or timetable objects with a Shape variable and attribute variables. For more information about geospatial tables, see "Create Geospatial Tables" on page 2-18.

Shapefiles

Geographic data structures most frequently originate when vector geodata is imported from a shapefile. The Environmental Systems Research Institute designed the shapefile format for vector geodata. Shapefiles encode coordinates for points, multipoints, lines, or polygons, along with non-geometrical attributes.

A shapefile stores attributes and coordinates in separate files; it consists of a main file, an index file, and an xBASE file. All three files have the same base name and are distinguished by the extensions .shp, .shx, and .dbf, respectively. (For example, given the base name 'concord_roads' the shapefile file names would be 'concord_roads.shp', 'concord_roads.shx', and 'concord_roads.dbf').

The Contents of Geographic Data Structures

The shaperead function reads vector features and attributes from a shapefile and returns a geographic data structure array. The shaperead function determines the names of the attribute fields at run-time from the shapefile xBASE table or from optional, user-specified parameters. If a shapefile attribute name cannot be directly used as a field name, shaperead assigns the field an appropriately modified name, usually by substituting underscores for spaces.

Field Name	Data Type	Description	Comments
Geometry	character vector	One of the following shape types: 'Point', 'MultiPoint', 'Line', or 'Polygon'.	For a 'PolyLine', the value of the <i>Geometry</i> field is simply 'Line'.
BoundingBox	2-by-2 numerical array	Specifies the minimum and maximum feature coordinate values in each dimension in the following form: $ \begin{bmatrix} \min(X) & \min(Y) \\ \max(X) & \max(Y) \end{bmatrix} $	Omitted for shape type 'Point'.
X, Y, Lon, or Lat	1-by-N array of class double	Coordinate vector.	
Attr	character vector or scalar number	Attribute name, type, and value.	Optional. There are usually multiple attributes.

The shaperead function does *not* support any 3-D or "measured" shape types: 'PointZ', 'PointM', 'MultipointZ', 'MultipointM', 'PolyLineZ', 'PolyLineM', 'PolygonZ', 'PolylineM', or 'Multipatch'. Also, although 'Null Shape' features can be present in a 'Point', 'Multipoint', 'PolyLine', or 'Polygon' shapefile, they are ignored.

PolyLine and Polygon Shapes

In geographic data structures with Line or Polygon geometries, individual features can have multiple parts—disconnected line segments and polygon rings. The parts can include counterclockwise inner rings that outline "holes." For an illustration of this, see "Create and Display Polygons" on page 2-8. Each disconnected part is separated from the next by a NaN within the X and Y (or Lat and Lon) vectors. You can use the isShapeMultipart function to determine if a feature has NaN-separated parts.

Each multipoint or NaN-separated multipart line or polygon entity constitutes a single feature and thus has one character vector or scalar double value per attribute field. It is not possible to assign distinct attributes to the different parts of such a feature; any character vector or numeric attribute imported with (or subsequently added to) the geostruct or mapstruct applies to all the feature's parts in combination.

Mapstructs and Geostructs

By default, shaperead returns a mapstruct containing X and Y fields. This is appropriate if the data set coordinates are already projected (in a map coordinate system). Otherwise, if the data set coordinates are unprojected (in a geographic coordinate system), use the parameter-value pair 'UseGeoCoords', true to make shaperead return a geostruct having Lon and Lat fields.

Coordinate Types. If you do not know whether a shapefile uses geographic coordinates or map coordinates, here are some things you can try:

• If the shapefile includes a projection file (.prj), use shapeinfo to get information about the coordinate reference system. If the CoordinateReferenceSystem field of the returned structure is a projcrs object, you have map coordinates. If the field is a geocrs object, you have geographic coordinates.

- If the shapefile does not include a projection file, use shapeinfo to obtain the BoundingBox. By looking at the ranges of coordinates, you may be able to tell what kind of coordinates you have.
- · Ask your data provider.

The geoshow function displays geographic features stored in geostructs, and the mapshow function displays geographic features stored in mapstructs. If you try to display a mapstruct with geoshow, the function issues a warning and calls mapshow. If you try to display a geostruct with mapshow, the function projects the coordinates with a Plate Carree projection and issues a warning.

Examining a Geographic Data Structure

Here is an example of an unfiltered mapstruct returned by shaperead:

```
S = shaperead('concord_roads.shp')
The output appears as follows:
S =
609x1 struct array with fields:
    Geometry
    BoundingBox
    X
    Y
    STREETNAME
    RT_NUMBER
    CLASS
    ADMIN_TYPE
    LENGTH
```

The shapefile contains 609 features. In addition to the Geometry, BoundingBox, and coordinate fields (X and Y), there are five attribute fields: STREETNAME, RT_NUMBER, CLASS, ADMIN_TYPE, and LENGTH.

```
Look at the 10th element:
```

```
S(10)
```

The output appears as follows:

```
ans =

Geometry: 'Line'
BoundingBox: [2x2 double]

X: [1x9 double]

Y: [1x9 double]

STREETNAME: 'WRIGHT FARM'

RT_NUMBER: '

CLASS: 5

ADMIN_TYPE: 0

LENGTH: 79.0347
```

This mapstruct contains 'Line' features. The tenth line has nine vertices. The values of the first two attributes are character vectors. The second happens to be an empty character vector. The final three attributes are numeric. Across the elements of S, X and Y can have various lengths, but STREETNAME and RT_NUMBER must always contain character vectors, and CLASS, ADMIN_TYPE and LENGTH must always contain scalar doubles.

In this example, shaperead returns an unfiltered mapstruct. If you want to filter out some attributes, see "Select Shapefile Data to Read" on page 2-99 for more information.

How to Construct Geographic Data Structures

Functions such as shaperead or gshhs return geostructs when importing vector geodata. However, you might want to create geostructs or mapstructs yourself in some circumstances. For example, you might *import* vector geodata that is not stored in a shapefile (for example, from a MAT-file, from an Microsoft® Excel® spreadsheet, or by reading in a delimited text file). You also might *compute* vector geodata and attributes by calling various MATLAB or Mapping Toolbox functions. In both cases, the coordinates and other data are typically vectors or matrices in the workspace. Packaging variables into a geostruct or mapstruct can make mapping and exporting them easier, because geographic data structures provide several advantages over coordinate arrays:

- All associated geodata variables are packaged in one container, a structure array.
- The structure is self-documenting through its field names.
- You can vary map symbology for points, lines, and polygons according to their attribute values by constructing a symbolspec for displaying the geostruct or mapstruct.
- A one-to-one correspondence exists between structure elements and geographic features, which extends to the children of hggroup objects constructed by mapshow and geoshow.

Achieving these benefits is not difficult. Use the following example as a guide to packaging vector geodata you import or create into geographic data structures.

Making Point and Line Geostructs

The following example first creates a point geostruct containing three cities on different continents and plots it with geoshow. Then it creates a line geostruct containing data for great circle navigational tracks connecting these cities. Finally, it plots these lines using a symbolspec.

Begin with a small set of point data, approximate latitudes and longitudes for three cities on three continents:

```
latparis = 48.87084; lonparis = 2.41306; % Paris coords
latsant = -33.36907; lonsant = -70.82851; % Santiago
latnyc = 40.69746; lonnyc = -73.93008; % New York City
```


- **2** Build a point geostruct; it needs to have the following required fields:
 - Geometry (in this case 'Point')
 - Lat (for points, this is a scalar double)
 - Lon (for points, this is a scalar double)

```
% The first field by convention is Geometry (dimensionality).
% As Geometry is the same for all elements, assign it with deal:
[Cities(1:3).Geometry] = deal('Point');
% Add the latitudes and longitudes to the geostruct:
Cities(1).Lat = latparis; Cities(1).Lon = lonparis;
Cities(2).Lat = latsant; Cities(2).Lon = lonsant;
Cities(3).Lat = latnyc; Cities(3).Lon = lonnyc;
% Add city names as City fields. You can name optional fields
% anything you like other than Geometry, Lat, Lon, X, or Y.
```

```
Cities(1).Name = 'Paris';
Cities(2).Name = 'Santiago';
Cities(3).Name = 'New York';
% Inspect your completed geostruct and its first member
Cities
Cities =
1x3 struct array with fields:
    Geometry
    Lat
    Lon
    Name
Cities(1)
ans =
    Geometry: 'Point'
         Lat: 48.8708
         Lon: 2.4131
        Name: 'Paris'
```


3 Display the geostruct on a Mercator projection of the Earth's land masses stored in the landareas.shp shapefile, setting map limits to exclude polar regions:

```
axesm('mercator','grid','on','MapLatLimit',[-75 75]); tightmap;
% Map the geostruct with the continent outlines
geoshow('landareas.shp')
% Map the City locations with filled circular markers
geoshow(Cities,'Marker','o',...
    'MarkerFaceColor','c','MarkerEdgeColor','k');
% Display the city names using data in the geostruct field Name.
% Note that you must treat the Name field as a cell array.
textm([Cities(:).Lat],[Cities(:).Lon],...
    {Cities(:).Name},'FontWeight','bold');
```



4 Next, build a Line geostruct to package great circle navigational tracks between the three cities:

```
% Call the new geostruct Tracks and give it a line geometry:
 [Tracks(1:3).Geometry] = deal('Line');
 % Create a text field identifying kind of track each entry is.
 % Here they all will be great circles, identified as 'gc'
 % (character vector used by certain functions to signify great circle arcs)
 trackType = 'gc';
 [Tracks.Type] = deal(trackType);
 % Give each track an identifying name
 Tracks(1).Name = 'Paris-Santiago';
 [Tracks(1).Lat Tracks(1).Lon] = ...
         track2(trackType, latparis, lonparis, latsant, lonsant);
 Tracks(2).Name = 'Santiago-New York';
 [Tracks(2).Lat Tracks(2).Lon] = ...
         track2(trackType, latsant, lonsant, latnyc, lonnyc);
 Tracks(3).Name = 'New York-Paris';
 [Tracks(3).Lat Tracks(3).Lon] = ...
         track2(trackType, latnyc, lonnyc, latparis, lonparis);
Compute lengths of the great circle tracks:
 % The distance function computes distance and azimuth between
 % given points, in degrees. Store both in the geostruct.
 for j = 1:numel(Tracks)
     [dist az] = ...
         distance(trackType,Tracks(j).Lat(1),...
                              Tracks(j).Lon(1),...
                             Tracks(j).Lat(end),...
                              Tracks(j).Lon(end));
     [Tracks(j).Length] = dist;
     [Tracks(j).Azimuth] = az;
 end
 % Inspect the first member of the completed geostruct
 Tracks(1)
 ans =
     Geometry: 'Line'
         Type: 'qc'
         Name: 'Paris-Santiago'
          Lat: [100x1 double]
          Lon: [100x1 double]
       Length: 104.8274
      Azimuth: 235.8143
Map the three tracks in the line geostruct:
 % On cylindrical projections like Mercator, great circle tracks
 % are curved except those that follow the Equator or a meridian.
 % Graphically differentiate the tracks by creating a symbolspec;
 % key line color to track length, using the 'summer' colormap.
% Symbolspecs make it easy to vary color and linetype by
 % attribute values. You can also specify default symbologies.
```



You can save the geostructs you just created as shapefiles by calling shapewrite with a file name of your choice, for example:

```
shapewrite(Cities, 'citylocs');
shapewrite(Tracks, 'citytracks');
```

Making Polygon Geostructs

Creating a geostruct or mapstruct for polygon data is similar to building one for point or line data. However, if your polygons include multiple, NaN-separated parts, recall that they can have only one value per attribute, not one value per part. Each attribute you place in a structure element for such a polygon pertains to all its parts. This means that if you define a group of islands, for example with a single NaN-separated list for each coordinate, all attributes for that element describe the islands as a group, not particular islands. If you want to associate attributes with a particular island, you must provide a distinct structure element for that island.

Be aware that the ordering of polygon vertices matters. When you map polygon data, the direction in which polygons are traversed has significance for how they are rendered by functions such as <code>geoshow</code> and <code>mapshow</code>. Proper directionality is particularly important if polygons contain holes. The Mapping Toolbox convention encodes the coordinates of outer rings (e.g., continent and island outlines) in clockwise order; counterclockwise ordering is used for inner rings (e.g., lakes and inland seas). Within the coordinate array, each ring is separated from the one preceding it by a NaN.

When plotted by mapshow or geoshow, clockwise rings are filled. Counterclockwise rings are unfilled; any underlying symbology shows through such holes. To ensure that outer and inner rings are correctly coded according to the above convention, you can invoke the following functions:

• ispolycw — True if vertices of polygonal contour are clockwise ordered

- poly2cw Convert polygonal contour to clockwise ordering
- poly2ccw Convert polygonal contour to counterclockwise ordering
- poly2fv Convert polygonal region to face-vertex form for use with patch in order to properly render polygons containing holes

Three of these functions check or change the ordering of vertices that define a polygon, and the fourth one converts polygons with holes to a completely different representation.

For an example of working with polygon geostructs, see "Converting Coastline Data (GSHHG) to Shapefile Format" on page 2-127.

Mapping Toolbox Version 1 Display Structures

Prior to Version 2, when geostructs and mapstructs were introduced, a different data structure was employed when importing geodata from certain external formats to encapsulate it for map display functions. These display structures accommodated both raster and vector map data and other kinds of objects, but lacked the generality of current geostructs and mapstructs for representing vector features and are being phased out of the toolbox. However, you can convert display structures that contain vector geodata to geostruct form using updategeostruct. For more information about Version 1 display structures and their usage, see "Version 1 Display Structures" in the reference page for displaym. Additional information is located in reference page for updategeostruct.

See Also

shaperead | shapeinfo

More About

"Create and Display Polygons" on page 2-8

Georeferenced Raster Data

Raster geodata consists of georeferenced data grids and images that are stored as matrices or objects in the MATLAB workspace. While raster geodata looks like any other matrix of real numbers, what sets it apart is that it is georeferenced, either to the globe or to a specified map projection, so that each pixel of data occupies a known patch of territory on the planet.

All regular data grids require a reference object, matrix, or vector, that specify the placement and resolution of the data set. Geolocated data grids do not require a separate reference object, as they explicitly identify the geographic coordinates of all rows and columns. For details on geolocated grids, see "Geolocated Data Grids" on page 2-39.

Reference Objects

A spatial reference object encapsulates the relationship between a geographic or planar coordinate system and a system of intrinsic coordinates anchored to the columns and rows of a 2-D spatially referenced raster grid or image. A reference object for raster data that is referenced to a geographic latitude-longitude system can be a GeographicCellsReference or

GeographicPostingsReference object. A referencing object for raster data referenced to a planar (projected) map coordinate system can be a MapCellsReference or MapPostingsReference object. Unlike the older referencing matrix and vector representations (described below), a reference object is self-documenting, providing a rich set of properties to describe both the intrinsic and extrinsic geometry. The use of reference objects is preferred, but some referencing matrix and vector functionality continues to be supported for the purpose of compatibility.

Referencing Matrices

A referencing matrix is a 3-by-2 matrix of doubles that describes the scaling, orientation, and placement of the data grid on the globe. For a given referencing matrix, R, one of the following relations holds between rows and columns and coordinates (depending on whether the grid is based on map coordinates or geographic coordinates, respectively):

```
[x y] = [row col 1] * R, or [long lat] = [row col 1] * R
```

Convert a referencing matrix to a raster reference object using the refmatToGeoRasterReference or refmatToMapRasterReference functions.

Referencing Vectors

In many instances (when the data grid or image is based on latitude and longitude and is aligned with the geographic graticule), a referencing matrix has more degrees of freedom than the data requires. In such cases, you may encounter a more compact representation, a three-element *referencing vector*. A referencing vector defines the pixel size and northwest origin for a regular, rectangular data grid:

```
refvec = [cells-per-degree north-lat west-lon]
```

This variable is often called refvec (or maplegend). The first element, cells-per-degree, describes the angular extent of each grid cell (e.g., if each cell covers five degrees of latitude and longitude, cells-per-degree would be specified as 0.2). Note that if the latitude extent of cells differs from their longitude extent you cannot use a referencing vector, and instead must specify a referencing object or

matrix. The second element, north-lat, specifies the northern limit of the data grid (as a latitude), and the third element, west-lon, specifies the western extent of the data grid (as a longitude). In other words, north-lat, west-lon is the northwest corner of the data grid. Note, however, that cell (1,1) is always in the southwest corner of the grid. This need not be the case for grids or images described by referencing objects or matrices.

Convert a referencing vector to a geographic raster reference object using the refvecToGeoRasterReference function.

Construct a Global Data Grid

Imagine an extremely coarse map of the world in which each cell represents 60°. Such a map matrix would be 3-by-6.

1 Create a 3-by-6 grid:

```
miniZ = [1 2 3 4 5 6; 7 8 9 10 11 12; 13 14 15 16 17 18];
```

2 Now make a referencing object:

```
miniR = georasterref('RasterSize', size(miniZ), ...
    'Latlim', [-90 90], 'Lonlim', [-180 180])
```

Your output appears like this:

miniR =

GeographicCellsReference with properties:

```
LatitudeLimits: [-90 90]
LongitudeLimits: [-180 180]
RasterSize: [3 6]
RasterInterpretation: 'cells'
ColumnsStartFrom: 'south'
RowsStartFrom: 'west'
CellExtentInLatitude: 60
CellExtentInLongitude: 60
RasterExtentInLatitude: 180
RasterExtentInLongitude: 360
XIntrinsicLimits: [0.5 6.5]
YIntrinsicLimits: [0.5 3.5]
CoordinateSystemType: 'geographic'
AngleUnit: 'degree'
```

3 Set up an equidistant cylindrical map projection:


```
figure('Color','white')
ax = axesm('MapProjection', 'eqdcylin');
axis off
setm(ax,'GLineStyle','-', 'Grid','on','Frame','on')
```

4 Draw a graticule with parallel and meridian labels at 60° intervals:

```
setm(ax, 'MlabelLocation', 60, 'PlabelLocation',[-30 30],...
   'MLabelParallel','north', 'MeridianLabel','on',...
   'ParallelLabel','on','MlineLocation',60,...
   'PlineLocation',[-30 30])
```

5 Map the data using **geoshow** and display with a color ramp and legend:

```
geoshow(miniZ, miniR, 'DisplayType', 'texturemap');
colormap('autumn')
colorbar
```



Note that the first row of the matrix is displayed at the bottom of the map, while the last row is displayed at the top.

Geolocated Data Grids

In addition to regular data grids, the toolbox provides another format for geodata: geolocated data grids. These multivariate data sets can be displayed, and their values and coordinates can be queried, but unfortunately much of the functionality supporting regular data grids is not available for geolocated data grids.

Regular data grids cover simple, regular quadrangles, that is, geographically rectangular and aligned with parallels and meridians. Geolocated data grids, in addition to these rectangular orientations, can have other shapes as well.

Define Geolocated Data Grid

To define a geolocated data grid, you must define three variables: a matrix of indices or values associated with the mapped region, a matrix giving cell-by-cell latitude coordinates, and a matrix giving cell-by-cell longitude coordinates.

Load a MAT-file containing an irregularly shaped geolocated data grid called mapmtx.

```
load mapmtx
```


View the variables created from this MAT-file. Two geolocated data grids are in this data set, each requiring three variables. The values contained in map1 correspond to the latitude and longitude coordinates, respectively, in ltl and lgl. Notice that all three matrices are the same size. Similarly, map2, lt2, and lg2 together form a second geolocated data grid. These data sets were extracted from the topo60c data grid. Neither of these maps is regular, because their columns do not run north to south.

whos

Name	Size	Bytes	Class	Attributes
description lg1 lg2 lt1 lt2 map1 map2	1x54 50x50 50x50 50x50 50x50 50x50 50x50	108 20000 20000 20000 20000 20000 20000	char double double double double double	
source	1x43	86	char	


Display the grids one after another to see their geography.

```
close all
axesm mercator
gridm on
framem on
h1 = surfm(lt1,lg1,map1);
h2 = surfm(lt2,lg2,map2);
```




Showing coastlines will help to orient you to these skewed grids. Notice that neither grid is a regular rectangle. One looks like a diamond geographically, the other like a trapezoid. The trapezoid is displayed in two pieces because it crosses the edge of the map. These shapes can be thought of as the geographic organization of the data, just as rectangles are for regular data grids. But, just as for regular data grids, this organizational logic does not mean that displays of these maps are necessarily a specific shape.

```
load coastlines
plotm(coastlat,coastlon,'r')
```



Now change the view to a polyconic projection with an origin at $0^{\circ}N$, $90^{\circ}E$. As the polyconic projection is limited to a 150° range in longitude, those portions of the maps outside this region are automatically trimmed.

```
setm(gca,'MapProjection','polycon','Origin',[0 90 0])
```



Geographic Interpretations of Geolocated Grids

Mapping Toolbox software supports three different interpretations of geolocated data grids:

- First, a map matrix having the same number of rows and columns as the latitude and longitude coordinate matrices represents the values of the map data at the corresponding geographic points (centers of data cells).
- Next, a map matrix having one fewer row and one fewer column than the geographic coordinate
 matrices represents the values of the map data within the area formed by the four adjacent
 latitudes and longitudes.
- Finally, if the latitude and longitude matrices have smaller dimensions than the map matrix, you can interpret them as describing a coarser *graticule*, or mesh of latitude and longitude cells, into which the blocks of map data are warped.

This section discusses the first two interpretations of geolocated data grids. For more information on the use of graticules, see "The Map Grid" on page 4-44.

Type 1: Values Associated with the Upper Left Grid Coordinate


As an example of the first interpretation, consider a 4-by-4 map matrix whose cell size is 30-by-30 degrees, along with its corresponding 4-by-4 latitude and longitude matrices:

```
Z = [ ...
1  2  3  4; ...
5  6  7  8; ...
9  10  11  12; ...
13  14  15  16];

lat = [ ...
30  30  30  30; ...
0  0  0  0; ...
-30  -30  -30  -30; ...
-60  -60  -60  -60];

lon = [ ...
0  30  60  90; ...
0  30  60  90; ...
0  30  60  90; ...
0  30  60  90; ...
0  30  60  90];
```

Display the geolocated data grid with the values of map shown at the associated latitudes and longitudes:




Notice that only 9 of the 16 total cells are displayed. The value displayed for each cell is the value at the upper left corner of that cell, whose coordinates are given by the corresponding lat and lon elements. By convention, the last row and column of the map matrix are not displayed, although they exist in the CData property of the surface object.

Type 2: Values Centered Within Four Adjacent Coordinates

For the second interpretation, consider a 3-by-3 map matrix with the same lat and lon variables:

```
delete(h)
delete(ht)
Z3by3 = [ ... ]
 1 2 3; ...
   5
      6; ...
 7
    8 9];
h = geoshow(lat,lon,Z3by3,'DisplayType','texturemap');
tlat = [ ...
   15 15 15; ...
   -15 -15 -15; ...
   -45 -45 -45];
tlon = [ ...
    15 45 75; ...
    15 45 75; ...
    15 45 74];
textm(tlat(:),tlon(:),num2str(Z3by3(:)), ...
    'Color','blue','FontSize',14)
```

Display a surface plot of the map matrix, with the values of map shown at the center of the associated cells:



All the map data is displayed for this geolocated data grid. The value of each cell is the value at the center of the cell, and the latitudes and longitudes in the coordinate matrices are the boundaries for the cells.

Ordering of Cells

You may have noticed that the first row of the matrix is displayed as the top of the map, whereas for a regular data grid, the opposite was true: the first row corresponded to the bottom of the map. This difference is entirely due to how the lat and lon matrices are ordered. In a geolocated data grid, the order of values in the two coordinate matrices determines the arrangement of the displayed values.

Transform Regular to Geolocated Grids

When required, a regular data grid can be transformed into a geolocated data grid. This simply requires that a pair of coordinate matrices be computed at the desired spatial resolution from the regular grid. For example, load elevation raster data and a geographic cells reference object. Then, create a latitude-longitude grid for the data by calling the geographicGrid function.

```
load topo60c
[lat,lon] = geographicGrid(topo60cR);
```

Transforming Geolocated to Regular Grids

Conversely, a regular data grid can also be constructed from a geolocated data grid. The coordinates and values can be embedded in a new regular data grid. The function that performs this conversion is geoloc2grid; it takes a geolocated data grid and a cell size as inputs.


Spatially Reference Imported Rasters

To associate the elements of a raster with geospatial locations, the raster must be accompanied by spatial referencing information such as the geographic or world limits, the distance between recorded samples, and the extent of individual cells. When a supported raster data file contains spatial referencing information, you can use the readgeoraster function to import the data as an array and the referencing information as a raster reference object. If the data file does not contain referencing information, then you can import the data as an array and create a reference object using the georefcells, georefpostings, maprefcells, or maprefpostings function. The creation function you use depends on characteristics of the raster data.

- **georefcells** The raster is a grid of quadrangular cells referenced to geographic latitude and longitude coordinates.
- georefpostings The raster is a grid of posting point samples referenced to geographic coordinates.
- maprefcells The raster is a grid of rectangular cells referenced to projected world *x* and *y*-coordinates.
- maprefpostings The raster is a grid of posting point samples referenced to projected coordinates.

Differentiate Between Cells and Postings

This image shows differences between a projected raster of cells and a projected raster of posting points. Both rasters have elements that are spaced 1 meter apart, with the raster covering *x*-values in the range [40,50] in meters and *y*-values in the range [20,28] in meters. The raster of cells is 8-by-10 and the raster of postings is 9-by-11. The boundary of the raster of cells is made up of the outermost boundaries of the outermost cells and the boundary of the raster of postings is made up of sampling points along the edges of the raster.



If you do not know whether your raster is a grid of cells or a grid of posting points, you can try the following:

- Ask your data provider.
- Search the metadata for information about the spatial registration or interpretation of the data. Metadata for rasters of cells can contain phrases such as "pixels" or "pixel is area." Metadata for rasters of posting points can contain phrases such as "grid", "node", or "pixel is point."
- Consider what the data represents. Images are typically made of cells, while elevation grids are typically made of posting points.
- Consider the size of the raster. If the dimensions of the raster are round numbers, such as a raster of size [1000 1000], then the raster is probably made of cells. If the dimensions of the raster are

round numbers plus one, such as a raster of size [1001 1001], then the raster is probably made of posting points.

Spatially Reference an Image

This example shows how to import an image, spatially reference the image by creating a reference object, then display the image on a map.

Import an image as an array by using the imread function. The array is of size 500-by-500-by-3 and specifies the red, green, and blue components of the image.

```
A = imread('boston_common.jpg');
```

To spatially reference the image, you must determine the following:

- Whether the image is referenced to geographic or projected coordinates
- Whether the image is made up of cells or posting points

Information included in the file boston_common.txt indicates that the image is referenced to projected coordinates and is made up of cells. Therefore, you can create a reference object by using the maprefcells function. Specify the x- and y-limits, also included in the file boston common.txt, using world coordinates.


```
xlimits = [235150 236150];
ylimits = [900100 901100];
R = maprefcells(xlimits,ylimits,size(A));
```

Define the first row of A as the northernmost edge of the image by setting the ColumnsStartFrom property of the reference object to 'north'. Otherwise, the ColumnsStartFrom property defaults to 'south'.

```
R.ColumnsStartFrom = 'north';
```

Display the spatially referenced image on a map by using the mapshow function.

```
mapshow(A,R)
```



The data used in this example is derived from data provided by MassGIS (Bureau of Geographic Information). See the file boston_common.txt for more details.

Spatially Reference an Elevation Grid

This example shows how to import elevation data, spatially reference the data by creating a reference object, then display the data on an axesm-based map.

Load elevation data as an array.

load elevation_n39_w106.mat

To spatially reference the data, you must determine the following:


- Whether the data is referenced to geographic or projected coordinates
- · Whether the data is made of cells or posting points

Information in the file elevation_n39_w106.txt indicates that the data set is referenced to geographic coordinates and is made up of posting points. Therefore, you can create a reference object for the data by using the georefpostings function. Specify the latitude and longitude limits, also included in the file boston_common.txt, using degrees.

```
latlim = [39 40];
lonlim = [-106 -105];
R = georefpostings(latlim,lonlim,size(elevation_n39_w106));
```

Create an axesm-based map by specifying the latitude and longitude limits of the data. Then, display the data as a surface by using the geoshow function. Apply a colormap appropriate for elevation data by using the demcmap function.

```
usamap(R.LatitudeLimits,R.LongitudeLimits)
geoshow(elevation_n39_w106,R,'DisplayType','surface')
demcmap(elevation_n39_w106)
```



The data set used in this example is derived from data provided by the U.S. Geological Survey. See the file elevation n39 w106.txt for more details.

See Also

Functions

readgeoraster | georefcells | georefpostings | maprefcells | maprefpostings

Objects

MapCellsReference | GeographicPostingsReference | GeographicCellsReference |
MapPostingsReference

Mosaic Spatially Referenced Raster Tiles

Geospatial raster data providers commonly package data as adjacent tiles. For example, SRTM Void Filled elevation data is packaged into 1-degree-by-1-degree tiles. To analyze data spread across several tiles, such as when calculating line-of-sight visibility, you must mosaic the tiles into a single raster.

The processes for combining rasters of cells and rasters of posting points are different. For information on differentiating rasters made up of cells and posting points, see "Spatially Reference Imported Rasters" on page 2-46.

Before mosaicking tiles, you must ensure that the tiles are adjacent and that the tile boundaries align. Otherwise, elements of the mosaicked raster can be spatially referenced to the wrong locations.

Mosaic Rasters of Cells

This example shows how to import two adjacent raster data files made of cells, mosaic the data into a single raster, and display the mosaicked raster on a map.

The files used in this example, concord_ortho_e.tif and concord_ortho_w.tif, contain east-west adjacent images with concord_ortho_e.tif to the east of concord_ortho_w.tif. The cell extents and world y-limits of the images are identical.

Import the images using the readgeoraster function. The outputs eastA and westA are arrays that contain the image data, and the outputs westR and eastR are MapCellsReference objects that contain spatial referencing information.

```
[eastA,eastR] = readgeoraster('concord_ortho_e.tif');
[westA,westR] = readgeoraster('concord_ortho_w.tif');
```

Create a mosaicked raster by combining the arrays. The images are adjacent and are made up of cells, so the eastern boundary of westA aligns with the western boundary of eastA.

```
mosaicA = [westA eastA];
```

Spatially reference the mosaicked raster by creating a raster reference object. You can create a reference object for a projected raster of cells by using the maprefcells function.

Specify the world x- and y-limits of the raster. The x-limits of the mosaicked raster are the minimum x-limit of the western raster and the maximum x-limit of the eastern raster. The world y-limits of the mosaicked raster are the same as the y-limits of the imported rasters. Create the reference object.


```
xlimits = [westR.XWorldLimits(1) eastR.XWorldLimits(2)];
ylimits = westR.YWorldLimits;
mosaicR = maprefcells(xlimits,ylimits,size(mosaicA));
```

The columns of arrays imported using the readgeoraster function start from the north. Therefore, set the ColumnsStartFrom property of the reference object to 'north'.

```
mosaicR.ColumnsStartFrom = 'north';
```

Display the mosaicked image on a map by using the mapshow function.

```
mapshow(mosaicA, mosaicR, 'DisplayType', 'image')
```



Mosaic Rasters of Postings

This example shows how to import two adjacent raster data files made of posting points, mosaic the data into a single raster, and display the mosaicked raster on a map.

The files used in this example, $n39_w106_3arc_v2.dt1$ and $n40_w106_3arc_v2.dt1$, contain north-south adjacent elevation grids with $n39_w106_3arc_v2.dt1$ to the south of $n40_w106_3arc_v2.dt1$. The northern latitude limit of the grid in $n39_w106_3arc_v2.dt1$ is the same as the southern latitude limit of the grid in $n40_w106_3arc_v2.dt1$. The spacing of posting points and the longitude limits of the grids are identical.

Import the grids using the readgeoraster function. The outputs southZ and northZ are arrays of type double that contain the elevation data, and the outputs southR and northR are GeographicPostingsReference objects that contain spatial referencing information.

```
[southZ,southR] = readgeoraster('n39_w106_3arc_v2.dt1','OutputType','double');
[northZ,northR] = readgeoraster('n40_w106_3arc_v2.dt1','OutputType','double');
```

Create a mosaicked raster by combining the arrays. The boundaries of posting point rasters are made up of the outermost posting points, and the columns of arrays imported using the readgeoraster function start from the north. Therefore, the southernmost row of northZ and the northernmost row of southZ are the same. To avoid a duplicate row in the mosaicked raster, remove the southernmost row of northZ before combining the arrays.

```
northZ(end,:) = [];
mosaicZ = [northZ; southZ];
```

Spatially reference the mosaicked raster by creating a raster reference object. You can create a reference object for a geographic raster of posting points by using the georefpostings function.

Specify the latitude and longitude limits of the raster. The latitude limits are the minimum latitude of the southern raster and the maximum latitude of the northern raster. The longitude limits of the mosaicked raster are the same as the longitude limits of the imported rasters. Create the reference object.


```
latlim = [southR.LatitudeLimits(1) northR.LatitudeLimits(2)];
lonlim = southR.LongitudeLimits;
mosaicR = georefpostings(latlim,lonlim,size(mosaicZ));
```

Set the ColumnsStartFrom and GeographicCRS properties of the reference object so that they match the properties of the imported reference objects.

```
mosaicR.ColumnsStartFrom = southR.ColumnsStartFrom;
mosaicR.GeographicCRS = southR.GeographicCRS;
```

Display the mosaicked raster on a map. Create a axesm-based map by specifying the latitude and longitude limits of the data. Then, display the data as a surface by using the geoshow function. Apply a colormap appropriate for elevation data by using the demcmap function.

```
usamap(mosaicR.LatitudeLimits,mosaicR.LongitudeLimits)
geoshow(mosaicZ,mosaicR,'DisplayType','surface')
demcmap(mosaicZ)
```



The elevation data used in this example is from the U.S. Geological Survey.

See Also

Functions

georefcells | georefpostings | maprefcells | maprefpostings | readgeoraster

Objects

MapCellsReference | GeographicPostingsReference | GeographicCellsReference |
MapPostingsReference

Related Examples

• "Spatially Reference Imported Rasters" on page 2-46

Unprojecting a Digital Elevation Model (DEM)

This example shows how to convert a USGS DEM into a regular latitude-longitude grid having comparable spatial resolution. U.S. Geological Survey (USGS) 30-meter Digital Elevation Models (DEMs) are regular grids (raster data) that use the UTM coordinate system. Using such DEMs in applications may require reprojecting and resampling them. You can readily apply the approach show here to projected map coordinate systems other than UTM and to other DEMs and most types of regular data grids.

Step 1: Import the DEM and its Metadata

This example uses a USGS DEM for a quadrangle 7.5-arc-minutes square located in the White Mountains of New Hampshire, USA. Import the data and a map cells reference object using the readgeoraster function. Get additional metadata using the georasterinfo function.

```
[Z,R] = readgeoraster('MtWashington-ft.grd','OutputType','double');
info = georasterinfo('MtWashington-ft.grd');
Replace missing data with NaN values.
m = info.MissingDataIndicator;
Z = standardizeMissing(Z,m);
```

Step 2: Get Projection Information

Get information about the projected coordinate reference system by querying the ProjectedCRS property of the reference object. The result is a projers object. Then, get the ellipsoid for the coordinate reference system.

```
p = R.ProjectedCRS;
ellipsoid = p.GeographicCRS.Spheroid
ellipsoid =
referenceEllipsoid with defining properties:
                 Code: 7008
                 Name: 'Clarke 1866'
           LengthUnit: 'meter'
        SemimajorAxis: 6378206.4
        SemiminorAxis: 6356583.8
    InverseFlattening: 294.978698213898
        Eccentricity: 0.0822718542230038
 and additional properties:
   Flattening
   ThirdFlattening
   MeanRadius
   SurfaceArea
   Volume
```

Step 3: Determine which UTM Zone to Use and Construct a Map

From the Name property of the projers object, you can tell that the DEM is gridded in a Universal Transverse Mercator (UTM) coordinate system.

```
ans =
   "UTM Zone 19, Northern Hemisphere"

To find the UTM zone, first locate the center of the DEM in UTM coordinates. Then, convert the coordinates to latitude-longitude.

[M,N] = size(Z);
```

```
xCenterIntrinsic = (1 + N)/2;
yCenterIntrinsic = (1 + M)/2;
[xCenter,yCenter] = intrinsicToWorld(R,xCenterIntrinsic,yCenterIntrinsic);
[latCenter,lonCenter] = projinv(p,xCenter,yCenter)

latCenter =
    44.3124

lonCenter =
```

Find the UTM zone for the DEM by using the utmzone function.


```
utmZone = utmzone(latCenter,lonCenter)
utmZone =
   '19T'
```

p.Name

-71.3126

Use the zone and ellipsoid to create an axesm-based map.

```
figure
axesm('utm','zone',utmZone,'geoid',ellipsoid)
axis off
gridm
mlabel on
plabel on
framem on
```




Note: if you can visually place the approximate location of New Hampshire on a world map, then you can confirm this result with the utmzoneui GUI.

utmzoneui(actualZone)

Step 4: Display the Original DEM on the Map


Use mapshow (rather than geoshow or meshm) to display the DEM on the map because the data are gridded in map (x-y) coordinates.

```
mapshow(Z,R,'DisplayType','texturemap')
demcmap(Z)
```



The DEM covers such a small part of this map that it may be hard to see (look between 44 and 44 degrees North and 72 and 71 degrees West), because the map limits are set to cover the entire UTM zone. You can reset them (as well as the map grid and label parameters) to get a closer look.

```
setm(gca,'MapLatLimit',[44.2 44.4],'MapLonLimit',[-71.4 -71.2])
setm(gca,'MLabelLocation',0.05,'MLabelRound',-2)
setm(gca,'PLabelLocation',0.05,'PLabelRound',-2)
setm(gca,'PLineLocation',0.025,'MLineLocation',0.025)
```



When it is viewed at this larger scale, narrow wedge-shaped areas of uniform color appear along the edge of the grid. These are places where Z contains the value NaN, which indicates the absence of actual data. By default they receive the first color in the color table, which in this case is dark green. These null-data areas arise because although the DEM is gridded in UTM coordinates, its data limits are defined by a latitude-longitude quadrangle. The narrow angle of each wedge corresponds to the non-zero "grid declination" of the UTM coordinate system in this part of the zone. (Lines of constant x run precisely north-south only along the central meridian of the zone. Elsewhere, they follow a slight angle relative to the local meridians.)

Step 5: Define the Output Latitude-Longitude Grid

The next step is to define a regularly-spaced set of grid points in latitude-longitude that covers the area within the DEM at about the same spatial resolution as the original data set.

First, you need to determine how the latitude changes between rows in the input DEM (i.e., by moving northward by 30 meters).

```
rng = R.CellExtentInWorldY; % In meters, consistent with p.LengthUnit
latcrad = deg2rad(latCenter); % latCenter in radians
% Change in latitude, in degrees
dLat = rad2deg(meridianfwd(latcrad,rng,ellipsoid) - latcrad)
dLat =
```

```
2,6998e-04
```

The actual spacing can be rounded slightly to define the grid spacing to be used for the output (latitude-longitude) grid.

```
gridSpacing = 1/4000; % In other words, 4000 samples per degree
```

To set the extent of the output (latitude-longitude) grid, start by finding the corners of the DEM in UTM map coordinates.

```
xCorners = R.XWorldLimits([1 1 2 2])'
yCorners = R.YWorldLimits([1 2 2 1])'

xCorners =

310380
310380
320730
320730

yCorners =

4901880
4916040
4916040
4901880
```

Then convert the corners to latitude-longitude. Display the latitude-longitude corners on the map (via the UTM projection) to check that the results are reasonable.


```
[latCorners, lonCorners] = projinv(p,xCorners, yCorners)
hCorners = geoshow(latCorners,lonCorners,'DisplayType','polygon',...
    'FaceColor','none','EdgeColor','red');

latCorners =

    44.2474
    44.3748
    44.3774
    44.2500

lonCorners =

    -71.3749
    -71.3801
    -71.2502
    -71.2454
```



Next, round outward to define an output latitude-longitude quadrangle that fully encloses the DEM and aligns with multiples of the grid spacing.

```
latSouth = gridSpacing * floor(min(latCorners)/gridSpacing)
lonWest = gridSpacing * floor(min(lonCorners)/gridSpacing)
latNorth = gridSpacing * ceil( max(latCorners)/gridSpacing)
lonEast = gridSpacing * ceil( max(lonCorners)/gridSpacing)

qlatlim = [latSouth latNorth];
qlonlim = [lonWest lonEast];

dlat = 100*gridSpacing;
dlon = 100*gridSpacing;
[latquad, lonquad] = outlinegeoquad(qlatlim, qlonlim, dlat, dlon);


hquad = geoshow(latquad, lonquad, ...
    'DisplayType','polygon','FaceColor','none','EdgeColor','blue');
snapnow;

latSouth =
    44.2473

lonWest =
```

-71.3803
latNorth = 44.3775
lonEast =

-71.2452



Finally, construct a geographic raster referencing object for the output grid. It supports transformations between latitude-longitude and the row and column subscripts. In this case, use of a world file matrix, W, enables exact specification of the grid spacing. Display W with more decimal places by temporarily changing the default display format.

```
0.00025
                                                                     -71.380125
                                             0.00025
                                                                      44.247375
nRows = round((latNorth - latSouth) / gridSpacing)
nCols = round(wrapTo360(lonEast - lonWest) / gridSpacing)
nRows =
   521
nCols =
   540
Rlatlon = georasterref(W,[nRows nCols],'cells');
Rlatlon.GeographicCRS = p.GeographicCRS
Rlatlon =
 GeographicCellsReference with properties:
             LatitudeLimits: [44.24725 44.3775]
            LongitudeLimits: [-71.38025 -71.24525]
                 RasterSize: [521 540]
       RasterInterpretation: 'cells'
           ColumnsStartFrom: 'south'
              RowsStartFrom: 'west'
       CellExtentInLatitude: 1/4000
      CellExtentInLongitude: 1/4000
     RasterExtentInLatitude: 0.13025
    RasterExtentInLongitude: 0.135
           XIntrinsicLimits: [0.5 540.5]
           YIntrinsicLimits: [0.5 521.5]
       CoordinateSystemType: 'geographic'
              GeographicCRS: [1x1 geocrs]
                  AngleUnit: 'degree'
```

Rlatlon fully defines the number and location of each cell in the output grid.

Step 6: Map Each Output Grid Point Location to UTM X-Y

Finally, you're ready to make use of the map projection, applying it to the location of each point in the output grid. First compute the latitudes and longitudes of those points, stored in 2-D arrays.

```
[rows,cols] = ndgrid(1:nRows, 1:nCols);
[lat,lon] = intrinsicToGeographic(Rlatlon,cols,rows);
```

Then apply the projection to each latitude-longitude pair, arrays of UTM x-y locations having the same shape and size as the latitude-longitude arrays.

```
[XI,YI] = projfwd(p,lat,lon);
```

At this point, XI(i,j) and YI(i,j) specify the UTM coordinate of the grid point corresponding to the i-th row and j-th column of the output grid.

Step 7: Resample the Original DEM


The final step is to use the MATLAB interp2 function to perform bilinear resampling.

At this stage, the value of projecting from the latitude-longitude grid into the UTM map coordinate system becomes evident: it means that the resampling can take place in the regular X-Y grid, making interp2 applicable. The reverse approach, unprojecting each (X,Y) point into latitude-longitude, might seem more intuitive but it would result in an irregular array of points to be interpolated -- a much harder task, requiring use of the far more costly griddata function or some rough equivalent.

```
[rows,cols] = ndgrid(1:M,1:N);
[X,Y] = intrinsicToWorld(R,cols,rows);
method = 'bilinear';
extrapval = NaN;
Zlatlon = interp2(X,Y,Z,XI,YI,method,extrapval);
```

View the result in the projected axes using geoshow, which will re-project it on the fly. Notice that it fills the blue rectangle, which is aligned with lines of latitude and longitude. (In contrast, the red rectangle, which outlines the original DEM, aligns with UTM x and y.) Also notice NaN-filled regions along the edges of the grid. The boundaries of these regions appear slightly jagged, at the level of a single grid spacing, due to round-off effects during interpolation. Move the red quadrilateral and blue quadrangle to the top, to ensure that they are not hidden by the raster display.

```
geoshow(Zlatlon,Rlatlon,'DisplayType','texturemap')
uistack([hCorners hquad],'top')
```



Credits

MtWashington-ft.grd (and supporting files):

United States Geological Survey (USGS) 7.5-minute Digital Elevation Model (DEM) for the Mt. Washington quadrangle, with elevation in meters. http://edc.usgs.gov/products/elevation/dem.html

For more information, run:

>> type MtWashington-ft.txt

See Also

 $refmat To Map Raster Reference \mid intrinsic To World \mid intrinsic To Geographic \mid georasterref \mid demcmap$

Georeferencing an Image to an Orthotile Base Layer

This example shows how to register an image to an earth coordinate system and create a new "georeferenced" image. It requires Image Processing Toolbox $^{\text{\tiny TM}}$ in addition to Mapping Toolbox $^{\text{\tiny TM}}$.

In this example, all georeferenced data are in the same earth coordinate system, the Massachusetts State Plane system (using the North American Datum of 1983 in units of meters). This defines our "map coordinates." The georeferenced data include an orthoimage base layer and a vector road layer.

The data set to be georeferenced is a digital aerial photograph covering parts of the village of West Concord, Massachusetts, collected in early spring, 1997.

Step 1: Render Orthoimage Base Tiles in Map Coordinates


The orthoimage base layer is structured into 4000-by-4000 pixel tiles, with each pixel covering exactly one square meter in map coordinates. Each tile is stored as a TIFF image with a world file. The aerial photograph of West Concord overlaps two tiles in the orthoimage base layer. (For convenience, this example actually works with two 2000-by-2000 sub-tiles extracted from the larger 4000-by-4000 originals. They have the same pixel size, but cover only the area of interest.)

Read the two orthophoto base tiles required to cover the extent of the aerial image.

```
[baseImage1,R1,cmap1] = readgeoraster("concord_ortho_w.tif");
[baseImage2,R2,cmap2] = readgeoraster("concord_ortho_e.tif");
Display the images in their correct spatial positions.

mapshow(baseImage1,cmap1,R1)
ax1 = gca;
mapshow(ax1,baseImage2,cmap2,R2)
title("Map View, Massachusetts State Plane Coordinates");
xlabel("Easting (meters)");
```

ylabel("Northing (meters)");



Step 2: Register Aerial Photograph to Map Coordinates

This step uses functions cpselect, cpstruct2pairs, fitgeotform2d, and imwarp, and method projtform2d/transformPointsForward, from the Image Processing Toolbox together with map raster reference objects from Mapping Toolbox. Together, they enable georegistration based on control point pairs that relate the aerial photograph to the orthoimage base layer.

Read the aerial photo.

```
inputImage = imread("concord_aerial_sw.jpg");
figure
imshow(inputImage)
title("Unregistered Aerial Photograph")
```



Unregistered Aerial Photograph

Both orthophoto images are indexed images but cpselect only takes grayscale images, so convert them to grayscale.

```
baseGray1 = im2uint8(ind2gray(baseImage1,cmap1));
baseGray2 = im2uint8(ind2gray(baseImage2,cmap2));
```

Downsample the images by a factor of 2, then pick two separate sets of control point pairs: one for points in the aerial image that appear in the first tile, and another for points that appear in the second tile. Save the control point pairs to the base workspace as control point structures named cpstruct1 and cpstruct2.

```
n = 2; % downsample by a factor n
load mapexreg.mat % load some points that were already picked
```

Optionally, edit or add to the pre-picked points using cpselect. Note that you need to work separately on the control points for each orthotile.

This tool helps you pick pairs of corresponding control points. Control points are landmarks that you can find in both images, like a road intersection, or a natural feature. Three pairs of control points have already been picked for each orthophoto tile. If you want to proceed with these points, go to Step 3: Infer and apply geometric transformation. If you want to add some additional pairs of points,

do so by identifying landmarks and clicking on the images. Save control points by choosing the **File** menu, then the **Save Points to Workspace** option. Save the points, overwriting variables cpstruct1 and cpstruct2.

Step 3: Infer and Apply Geometric Transformation

Extract control point pairs from the control point structures.

```
[input1,base1] = cpstruct2pairs(cpstruct1);
[input2,base2] = cpstruct2pairs(cpstruct2);
```

Account for downsampling by factor n.


```
input1 = n*input1 - 1;
input2 = n*input2 - 1;
base1 = n*base1 - 1;
base2 = n*base2 - 1;
```

Transform base image coordinates into map (State Plane) coordinates.

```
[x1, y1] = intrinsicToWorld(R1,base1(:,1),base1(:,2));
[x2, y2] = intrinsicToWorld(R2,base2(:,1),base2(:,2));
```


Combine the two sets of control points and infer a projective transformation. (The projective transformation should be a reasonable choice, since the aerial image is from a frame camera and the terrain in this area is fairly gentle.)

```
input = [input1; input2];
spatial = [x1 y1; x2 y2];
tform = fitgeotform2d(input,spatial, "projective")
tform =
  projtform2d with properties:
    Dimensionality: 2
                 A: [3×3 double]
Compute and plot (2D) residuals.
residuals = transformPointsForward(tform, input) - spatial;
figure
plot(residuals(:,1),residuals(:,2),"+")
title("Control Point Residuals");
xlabel("Easting offset (meters)");
ylabel("Northing offset (meters)");
xlim([-4 4])
ylim([-4 4])
axis equal
```



Predict corner locations for the registered image, in map coordinates, and connect them to show the image outline.

```
mInput = size(inputImage,1);
nInput = size(inputImage,2);
inputCorners = 0.5 ...
    + [0
                0;
       0
                mInput;
       nInput
                mInput;
       nInput
                0];
outputCornersSpatial = transformPointsForward(tform, inputCorners);
outputCornersX = outputCornersSpatial(:,1);
outputCornersY = outputCornersSpatial(:,2);
figure(ax1.Parent)
line(outputCornersX,outputCornersY, "Color", "w")
```



Calculate the average pixel size of the input image (in map units).

```
pixelSize = [hypot( ...
    outputCornersX(2) - outputCornersX(1), ...
    outputCornersY(2) - outputCornersY(1)) / mInput, ...
hypot( ...
    outputCornersX(4) - outputCornersX(5), ...
    outputCornersY(4) - outputCornersY(5)) / nInput]

pixelSize =
    0.9096    0.8905
```

Variable pixelSize gives a starting point from which to select a width and height for the pixels in our georegistered output image. In principle we could select any size at all for our output pixels. However, if we make them too small we waste memory and computation time, ending up with a big (many rows and columns) blurry image. If we make them too big, we risk aliasing the image as well as needlessly discarding information in the original image. In general we also want our pixels to be square. A reasonable heuristic is to select a pixel size that is slightly larger than max(pixelSize) and is a "reasonable" number (i.e., 0.95 or 1.0 rather than 0.9096). Here we chose 1, which means that each pixel in our georegistered image will cover one square meter on the ground. It's "nice" to have georegistered images that align along integer map coordinates for display and analysis.

```
outputPixelSize = 1;
```

Choose world limits that are integer multiples of the output pixel size.

```
xWorldLimits = outputPixelSize ...
  * [floor(min(outputCornersX) / outputPixelSize), ...
      ceil(max(outputCornersX) / outputPixelSize)]


yWorldLimits = outputPixelSize ...
  * [floor(min(outputCornersY) / outputPixelSize), ...
      ceil(max(outputCornersY) / outputPixelSize)]

xWorldLimits =
    208154    209693

yWorldLimits =
    911435    912583
```

Display a bounding box for the registered image.

line(xWorldLimits([1 1 2 2 1]),yWorldLimits([2 1 1 2 2]),"Color","red")



The dimensions of the registered image will be as follows:

```
mOutput = diff(yWorldLimits) / outputPixelSize
nOutput = diff(xWorldLimits) / outputPixelSize
```

```
mOutput = 1148

nOutput = 1539
```

Create an Image Processing Toolbox referencing object for the registered image.

```
R = imref2d([mOutput nOutput],xWorldLimits,yWorldLimits)
```

Create a map raster reference object, which is the Mapping Toolbox counterpart to an Image Processing Toolbox referencing object.

```
Rmap = maprefcells(R.XWorldLimits,R.YWorldLimits, R.ImageSize, ...
    "ColumnsStartFrom", "north")
Rmap =
 MapCellsReference with properties:
            XWorldLimits: [208154 209693]
             YWorldLimits: [911435 912583]
              RasterSize: [1148 1539]
    RasterInterpretation: 'cells'
        ColumnsStartFrom: 'north'
           RowsStartFrom: 'west'
      CellExtentInWorldX: 1
      CellExtentInWorldY: 1
    RasterExtentInWorldX: 1539
    RasterExtentInWorldY: 1148
        XIntrinsicLimits: [0.5 1539.5]
        YIntrinsicLimits: [0.5 1148.5]
    TransformationType: 'rectilinear'
CoordinateSystemType: 'planar'
            ProjectedCRS: []
```

Apply the geometric transformation using imwarp. Flip its output so that the columns run from north to south.

```
registered = flipud(imwarp(inputImage, tform,"OutputView",R));
figure
imshow(registered)
```



You can write the registered image as a TIFF with a world file, thereby georeferencing it to our map coordinates.

```
imwrite(registered, "concord_aerial_sw_reg.tif");
worldfilewrite(Rmap,getworldfilename("concord_aerial_sw_reg.tif"));
```


Step 4: Display the Registered Image in Map Coordinates

Display the registered image on the same (map coordinate) axes as the orthoimage base tiles. The registered image does not completely fill its bounding box, so it includes null-filled triangles. Create an alpha data mask to make these fill areas render as transparent.

```
alphaData = registered(:,:,1);
alphaData(alphaData~=0) = 255;

figure
mapshow(baseImage1,cmap1,R1)
ax2 = gca;
mapshow(ax2,baseImage2,cmap2,R2)
title("Map View, Massachusetts State Plane Coordinates");
xlabel("Easting (meters)");
```

```
ylabel("Northing (meters)");
mInput = mapshow(ax2,registered,Rmap);
mInput.AlphaData = alphaData;
```



You can assess the registration by looking at features that span both the registered image and the orthophoto images.


Step 5: Overlay Vector Road Layer (from Shapefile)

Use shapeinfo and readgeotable to learn about the attributes of the vector road layer. Render the roads on the same axes and the base tiles and registered image.

```
roadsfile = "concord_roads.shp";
roadinfo = shapeinfo(roadsfile);
roads = readgeotable(roadsfile);
```

Create symbolization based on the CLASS attribute (the type of road). Note that very minor roads have CLASS values equal to 6, so don't display them.

```
roadspec = makesymbolspec("Line",{'CLASS',6,'Visible','off'});
mapshow(ax2,roads,"SymbolSpec",roadspec,"Color","cyan")
```



Observe that the roads line up quite well with the roads in the images. Two obvious linear features in the images are not roads but railroads. The linear feature that trends roughly east-west and crosses both base tiles is the Fitchburg Commuter Rail Line of the Massachusetts Bay Transportation Agency. The linear feature that trends roughly northwest-southeast is the former Framingham-Lowell secondary line.

Credits

```
Office of Geographic and Environmental Information (MassGIS), Commonwealth of Massachusetts Executive Office of Environmental Affairs http://www.state.ma.us/mgis
```

For more information, run:

- >> type concord_ortho.txt
- >> type concord_roads.txt

concord aerial sw.jpg

Visible color aerial photograph courtesy of mPower3/Emerge.

concord orthow w.tif, concord ortho e.tif, concord roads.shp:

For more information, run:

>> type concord_aerial_sw.txt

See Also

Functions

 $readgeoraster \mid im2uint8 \mid cpstruct2pairs \mid intrinsicToWorld \mid fitgeotform2d \mid transformPointsForward \mid imref2d$

Objects

MapCellsReference

Find Geospatial Data Online

Many vector and raster data formats have been developed for storing geospatial data. With Mapping Toolbox you can read geodata files in general purpose formats (e.g., Esri® shapefile, GeoTIFF, and SDTS DEM) that a variety of mapping and image processing applications also read and write. You can also read files that are in a variety of special formats designed to exchange specific sets or kinds of geodata (e.g., GSHHG, VMAP0, DEM, and DTED files). You can order, and in many cases, download such data over the Internet.

Mapping Toolbox provides generalized sample data in the form of data files for the entire Earth and its major regions, as well as some higher resolution files covering small areas. These data sets are frequently used in the code examples provided in the Mapping Toolbox documentation. You can find them in <code>matlabroot/examples/map/data</code> and <code>matlabroot/toolbox/map/mapdata</code>. You can list them, along with their metadata, by typing the following at the command line:

```
ls(fullfile(matlabroot,'examples','map','data'))
ls(fullfile(matlabroot,'toolbox','map','mapdata'))
```

In addition, the worlddatamap function, available on MATLAB Central, allows you to use worldmap to map a region using data from a shapefile or data grid. Examples of worlddatamap and world vector data in shapefile format are available under the heading worlddatamap Examples.

For information about a small but useful subset of geodata resources on the Internet, see the following topics:

Note MathWorks does not warrant the accuracy, timeliness, or fitness for use of any data set listed in these topics, and makes no endorsement of any data vendor mentioned.

- "Find Geospatial Vector Data" on page 2-78 Lists URLs from which you can obtain vector (point, line, or polygon) geospatial data sets and data products, such as Esri shape files.
- "Find Geospatial Raster Data" on page 2-79 Lists URLs from which you can obtain raster (gridded) geospatial data sets and data products, such as Digital Terrain Elevation Data (DTED). This topic also covers raster maps from Web Map Service servers.

Note If you are viewing this documentation installed locally (controlled by your Documentation location preference), you should also consult "Find Geospatial Data Online" on page 2-77 on the MathWorks website for possible updates and corrections.

Find Geospatial Vector Data

Find and download geospatial vector (point, line, or polygon) data using resources such as the ones in these tables. For information about supported file formats, see the readgeotable function.

Note If you are using a Macintosh system and the links on this page do not work, open the Mapping Toolbox documentation in a separate browser and view this section there. You can find this topic by searching for "Find Geospatial Vector Data".

Resource	Provider	Examples of Products and Data Sets
The National Map Download Application	US Geological Survey (USGS)	USGS National Boundary Dataset
Advanced Weather Interactive Processing System (AWIPS) Basemap Shapefiles	National Oceanic and Atmospheric Administration (NOAA)	Canada provincial boundaries (data link), Mexico state boundaries (data link)
Geography Program	US Census	TIGER/Line shapefiles and geodatabases, cartographic boundary files
Data.gov	US General Services Administration	Agriculture, climate, energy, local government
NOAA Shoreline Website	NOAA	US coastlines, historical data
Shoreline / Coastline Resources	NOAA and National Centers for Environmental Information (NCEI)	Global Self-Consistent Hierarchical High-Resolution Geography (GSHHG) (read using the gshhs function)

See Also

Functions

readgeotable | readtable | shaperead | shapeinfo

See Also

More About

- "Find Geospatial Data Online" on page 2-77
- "Find Geospatial Raster Data" on page 2-79

Find Geospatial Raster Data

In this section...

"Download Data" on page 2-79

"Use Web Map Service Data" on page 2-80

Get geospatial raster data over the Internet by downloading it or by accessing the Web Map Service (WMS) database.

Download Data

Find and download geospatial raster data using resources such as the ones in these tables. For information about supported file formats, see readgeoraster and worldfileread.

Note If you are using a Macintosh system and the links on this page do not work, open the Mapping Toolbox documentation in a separate browser and view this section there. You can find this topic by searching for "Find Geospatial Raster Data".

Elevation

Resource	Provider	Examples of Products and Data Sets
EarthExplorer	US Geological Survey (USGS)	DTED, GMTED2010, GTOPO30
The National Map Download Application	USGS	3DEP
Data.gov	US General Services Administration	DTED, 3DEP, GMTED2010
ETOPO1 Global Relief Model	National Oceanic and Atmospheric Administration (NOAA) and National Centers for Environmental Information (NCEI)	ETOPO1 (use GeoTIFF format)
GMTED2010 Viewer	USGS	GMTED2010
The Global Land One-km Base Elevation Project	NOAA and NCEI	GLOBE
Global Topography	Scripps Institution of Oceanography	Smith and Sandwell

Land Cover Classification

Resource		Examples of Products and Data Sets
EarthExplorer	USGS	GLCC, AVHRR

Resource	Provider	Examples of Products and Data Sets
Digital Coast Data Access Viewer	NOAA Office for Coastal Management	C-CAP Regional Land Cover and Change
Data.gov	US General Services Administration	GLCC, AVHRR

Imagery

Resource	Provider	Examples of Products and Data Sets
EarthExplorer	USGS	Landsat
Digital Coast Data Access Viewer	NOAA Office for Coastal Management	High-Resolution Orthoimagery
Data.gov	US General Services Administration	Landsat

Use Web Map Service Data

Mapping Toolbox includes a built-in database of prequalified Web Map Service (WMS) servers and layers. Search the WMS database for layers using the wmsfind function. Read layers from the database using the wmsread function.

See Also

readgeoraster | worldfileread

Functions that Read and Write Geospatial Data

The following table lists Mapping Toolbox functions that read geospatial data products and file formats and write geospatial data files. Note that the <code>geoshow</code> and <code>mapshow</code> functions can read and display both vector and raster geodata files in several formats. Click function names to see their details in the Mapping Toolbox reference documentation. The **Type of Coordinates** column describes whether the function returns or writes data in geographic ("geo") or projected ("map") coordinates, or as geolocated data grids (which, for the functions listed, all contain geographic coordinates). Some functions can return either geographic or map coordinates, depending on what the file being read contains; these functions do not signify what type of coordinates they return (in the case of shaperead, however, you can specify whether the structure it returns should have X and Y or Lon and Lat fields).

Function	Description	Type of Data	Type of Coordinates
avhrrgoode	Read data products derived from the Advanced Very High Resolution Radiometer (AVHRR) and stored in the Goode Homosoline projection: Global Land Cover Classification (GLCC) or Normalized Difference Vegetation Index (NDVI)	raster	geolocated
avhrrlambert	Read AVHRR GLCC and NDVI data products stored in the Lambert Conformal Conic projection	raster	geolocated
dteds	List DTED data grid file names for a specified latitude-longitude quadrangle	file names	geo
egm96geoid	Read 15-minute gridded geoid heights from the EGM96 geoid model	raster	geo
georasterinfo	Get information about data files in formats such as Esri Binary Grid, Esri GridFloat, DTED, GeoTIFF, and GPX	raster	map geo
geotiffinfo	Get information about GeoTIFF files	properties	map geo
geotiffwrite	Write GeoTIFF file	raster	map geo
getworldfilename	Derive a world file name from an image file name	file name	geo map
globedems	List GLOBE data file names for a specified latitude-longitude quadrangle	file names	geo
gshhs	Read Global Self-Consistent Hierarchical High-Resolution Geography (GSHHG) data	vector	geo
gtopo30s	List GTOPO30 data file names for a specified latitude-longitude quadrangle	file names	geo

Function	Description	Type of Data	Type of Coordinates
kmlwrite	Write vector coordinates and attributes to a file in KML format	vector points and attributes	geo
readgeoraster	Read data in formats such as Esri Binary Grid, Esri GridFloat, DTED, GeoTIFF, and GPX	raster	geo map
readgeotable	Read data in formats such as shapefile, GPX, Esri file geodatabase, KML, and GeoJSON	vector	geo map
sdtsinfo	Get information about SDTS data set	properties	geo
shapeinfo	Get information about the geometry and attributes of geographic features stored in a shapefile (a set of ".shp", ".shx" and ".dbf" files)	properties	geo map
shaperead	Read geographic feature coordinates and associated attributes from a shapefile	vector	geo map
shapewrite	Write geospatial data and associated attributes in shapefile format	vector	geo map
usgsdems	List USGS digital elevation model (DEM) file names covering a specified latitude-longitude quadrangle	file names	map
vmap0data	Extract selected data from the Vector Map Level 0 (VMAP0) CD-ROMs	vector	geo
vmap0read	Read a VMAP0 file	vector	geo
vmap0rhead	Read VMAP0 file headers	properties	geo
worldfileread	Read a world file and return a referencing matrix	georeferencing information	geo
worldfilewrite	Export a referencing matrix into an equivalent world file	georeferencing information	geo

The MATLAB environment provides many general file reading and writing functions (for example, imread, imwrite, urlread, and urlwrite) which you can use to access geospatial data you want to use with Mapping Toolbox software. For example, you can read a TIFF image with imread and its accompanying world file with worldfileread to import the image and construct a referencing matrix to georeference it. See the Mapping Toolbox example "Georeferencing an Image to an Orthotile Base Layer" on page 2-65 for an example of how you can do this.

Export Vector Geodata

When you want to share geodata you are working with, Mapping Toolbox functions can export it two principal formats, shapefiles and KML files. Shapefiles are binary files that can contain point, line, vector, and polygon data plus attributes. Shapefiles are widely used to exchange data between different geographic information systems. KML files are text files that can contain the same type of data, and are used mainly to upload geodata the Web. The toolbox functions shapewrite and kmlwrite export to these formats.

To format attributes, shapewrite uses an auxiliary structure called a *DBF spec*, which you can generate with the makedbfspec function. Similarly, you can provide attributes to kmlwrite to format as a table by providing an *attribute spec*, a structure you can generate using the makeattribspec function or create manually.

For examples of and additional information about reading and writing shapefiles and DBF specs, see the documentation for shapeinfo, shaperead, shapewrite, and makedbfspec. The example provided in "How to Construct Geographic Data Structures" on page 2-30 also demonstrates exporting vector data using shapewrite. For information about creating KML files, see "Export KML Files for Viewing in Earth Browsers" on page 2-95.

Exporting Vector Data to KML

This example shows how to structure geographic point, line, and polygon vector data and export it to a Keyhole Markup Language (KML) file. KML is an XML-based markup language designed for visualizing geographic data on Web-based maps or "Earth browsers", such as Google Earth $^{\text{TM}}$, Google Maps $^{\text{TM}}$, NASA WorldWind, and the ESRI $^{\text{RM}}$ ArcGIS $^{\text{TM}}$ Explorer.

The following functions write geographic data to a KML file:

- kmlwritepoint Write geographic points to KML file
- kmlwriteline Write geographic line to KML file
- kmlwritepolygon Write geographic polygon to KML file
- kmlwrite Write geographic data to KML file

Define an Output Folder for the KML Files

This example creates several KML files and uses the variable kmlFolder to denote their location. The value used here is determined by the output of the tempdir command, but you could easily customize this.

```
kmlFolder = tempdir;
```

Create a cell array of the KML file names used in this example in order to optionally remove them from your KML output folder when the example ends.

```
kmlFilenames = {};
```

Create a Function Handle to Open an Earth Browser

A KML file can be opened in a variety of "Earth browsers", Web maps, or an editor. You can customize the following anonymous function handle to open a KML file. Executing this function handle launches the Google Earth browser, which must be installed on your computer. You can use the application by assigning the variable useApplication to true in your workspace or assign it to true here.

```
useApplication = exist('useApplication','var') && useApplication;
if useApplication
    if ispc
        % On Windows(R) platforms display the KML file with:
        openKML = @(filename) winopen(filename);
    elseif ismac
        % On Mac platforms display the KML file with:
        cmd = 'open -a Google\ Earth ';
        openKML = @(filename) system([cmd filename]);
    else
        % On Linux platforms display the KML file with:
        cmd = 'googleearth ';
        openKML = @(filename) system([cmd filename]);
    end
else
    % No "Earth browser" is installed on the system.
    openKML = @(filename) disp('');
end
```

Example 1: Write Single Point to KML File

This example writes a single point to a KML file.

Assign latitude and longitude values for Paderborn, Germany.

```
lat = 51.715254;
lon = 8.75213;

Use kmlwritepoint to write the point to a KML file.
filename = fullfile(kmlFolder, 'Paderborn.kml');
kmlwritepoint(filename,lat,lon);

Open the KML file.
openKML(filename)

Add filename to kmlFilenames.
kmlFilenames{end+1} = filename;
```

Example 2: Write Single Point to KML File with Icon and Description

This example writes a single point to a KML file. The placemark includes an icon and a description with HTML markup.

Assign latitude and longitude coordinates for a point that locates the headquarters of MathWorks® in Natick, Massachusetts.

```
lat = 42.299827;
lon = -71.350273;
```

Create a description for the placemark. Include HTML tags in the description to add new lines for the address.

```
description = sprintf('%s<br>%s</br></br></ra>
'3 Apple Hill Drive', 'Natick, MA. 01760', ...
'https://www.mathworks.com');

Assign iconFilename to a GIF file on the local system's network.

iconDir = fullfile(matlabroot, 'toolbox', 'matlab', 'icons');
iconFilename = fullfile(iconDir, 'matlabicon.gif');

Assign the name for the placemark.

name = 'The MathWorks, Inc.';

Use kmlwritepoint to write the point and associated data to the KML file.

filename = fullfile(kmlFolder, 'MathWorks.kml');
kmlwritepoint(filename, lat, lon, 'Description', description, 'Name', name, ...
'Icon', iconFilename);

Open the KML file.

openKML(filename)
```

```
Add filename to kmlFilenames.
```

```
kmlFilenames{end+1} = filename;
```

Max Height: [1x1 struct]

Example 3: Write Multiple Points to KML File

This example writes the locations of cities in France to a KML file, including the names of the cities, and removes the default description table.

Read world cities data from the shapefile called worldcities.shp into a geospatial table. Create a subtable containing the data for cities in France.

```
worldcities = readgeotable("worldcities.shp");
n = ["Paris" "Lyon" "Nantes" "Bordeaux" "Marseille"];
rows = ismember(worldcities.Name,n);
cities = worldcities(rows,:);
```

Write the data in the subtable to a KML file by using kmlwrite. Assign the name of the placemark to the name of the city. Remove the default description since the data has only one attribute.

```
filename = fullfile(kmlFolder,'French_Cities.kml');
kmlwrite(filename,cities,'Name',cities.Name,'Description',{});
Open the KML file.
openKML(filename)
Add filename to kmlFilenames.
kmlFilenames{end+1} = filename;
```

Example 4: Write Multiple Points to KML File with Modified Attribute Table

This example writes placemarks at the locations of tsunami (tidal wave) events, reported over several decades and tagged geographically by source location, to a KML file.

Read the data from the shapefile called tsunamis.shp as a geospatial table.

Rename the Max_Height attribute to Maximum Height and highlight each attribute label in bold font.

```
attribspec.Max_Height.AttributeLabel = "<b>Maximum Height</b>";
attribspec.Cause.AttributeLabel = "<b>Cause</b>";
attribspec.Year.AttributeLabel = "<b>Year</b>";
attribspec.Location.AttributeLabel = "<b>Location</b>";
attribspec.Country.AttributeLabel = "<b>Country</b>";
```

Add Meters to the format of the maximum height attribute. Set the format of the year attribute to include no decimal places.

```
attribspec.Max_Height.Format = "%.1f Meters";
attribspec.Year.Format = "%.0f";
```

Export the selected attributes and tsunami source locations to a KML file by using the kmlwrite function.

```
filename = fullfile(kmlFolder, 'Tsunami_Events.kml');
name = tsunamis.Location;
kmlwrite(filename,tsunamis, 'Description',attribspec,'Name',name)

Open the KML file.

openKML(filename)

Add filename to kmlFilenames.
kmlFilenames{end+1} = filename;
```

Example 5: Write Single Point with a LookAt Virtual Camera to KML File

This example writes a single point with a LookAt virtual camera near Machu Picchu, Peru

Use a geopoint vector to define a LookAt virtual camera.

lat = -13.163111;

```
lon = -72.544945;
lookAt = geopoint(lat,lon);
lookAt.Range = 1500;
lookAt.Heading = 260;
lookAt.Tilt = 67;

Use kmlwritepoint to write the point location and LookAt information.

filename = fullfile(kmlFolder, 'Machu_Picchu.kml');
alt = 2430;
name = 'Machu_Picchu';
kmlwritepoint(filename,lat,lon,alt,'LookAt',lookAt,'Name',name);

Open the KML file.

openKML(filename)

Add filename to kmlFilenames.

kmlFilenames{end+1} = filename;
```

Example 6: Write Single Point with a Camera to KML File

This example writes a single point with a camera view of the Washington Monument in Washington D.C to a KML file. The marker is placed at the ground location of the camera.

Construct the camera.

```
camlat = 38.889301;
camlon = -77.039731;
camera = geopoint(camlat,camlon);
camera.Altitude = 500;
camera.Heading = 90;
camera.Tilt = 45;
camera.Roll = 0;
```

Use kmlwritepoint to write the point location and Camera information.

```
name = 'Camera ground location';
lat = camera.Latitude;
lon = camera.Longitude;
filename = fullfile(kmlFolder, 'WashingtonMonument.kml');
kmlwritepoint(filename, lat, lon, 'Camera', camera, 'Name', name)
Open the KML file.
```

Add filename to kmlFilenames.

openKML(filename)

kmlFilenames{end+1} = filename;

Example 7: Write Address Data to KML File

This example writes unstructured address data to a KML file.

Create a cell array containing names of several places of interest in the Boston area.

```
names = {'Boston', ...
    'Massachusetts Institute of Technology', ...
    'Harvard University', ...
    'Fenway Park', ...
    'North End'};
```

Create a cell array containing addresses for the places of interest in the Boston area.

```
addresses = { ...
    'Boston, MA', ...
    '77 Massachusetts Ave, Cambridge, MA 02139', ...
    'Massachusetts Hall, Cambridge MA 02138', ...
    '4 Yawkey Way, Boston, MA', ...
    '134 Salem St, Boston, MA'};
```

Use a Google Maps icon for each of the placemarks.

```
icon = 'http://maps.google.com/mapfiles/kml/paddle/red-circle.png';
```

Use kmlwrite to write the cell array of addresses to the KML file.

```
filename = fullfile(kmlFolder, 'Places_of_Interest.kml');
kmlwrite(filename,addresses,'Name',names,'Icon',icon,'IconScale',1.5);
Open the KML file.
openKML(filename)
Add filename to kmlFilenames.
kmlFilenames{end+1} = filename;
```

Example 8: Write Single Line to KML File

This example writes a single line connecting the top of Mount Washington to the Mount Washington Hotel in Carroll, New Hampshire, to a KML file.

Assign coordinate values for the region of interest.

```
lat Mount Washington = 44.270489039;
lon Mount Washington = -71.303246453;
lat Mount Washington Hotel = 44.258056;
lon_Mount_Washington_Hotel = -71.440278;
lat = [lat_Mount_Washington lat_Mount_Washington_Hotel];
lon = [lon_Mount_Washington lon_Mount_Washington_Hotel];
Set the altitude to 6 feet, for the approximate height of a person.
alt = 6 * unitsratio('meters', 'feet');
Add a camera viewpoint from the Mount Washington Hotel.
clat = lat(2);
clon = lon(2);
camera = geopoint(clat,clon,'Altitude',2,'Tilt',90,'Roll',0,'Heading',90);
Use kmlwriteline to write the arrays to a KML file.
filename = fullfile(kmlFolder, 'Mount Washington.kml');
name = 'Mount Washington';
kmlwriteline(filename,lat,lon,alt,'Name',name,'Color','k','Width',3, ...
    'Camera',camera,'AltitudeMode','relativeToGround');
Open the KML file.
openKML(filename)
Add filename to kmlFilenames.
kmlFilenames{end+1} = filename;
```

Example 9: Write GPS Track Log to KML File

This example writes a GPS track log to a KML file.

Read the track points log from the GPX file. The data in the log was obtained from a GPS wristwatch held while gliding over Mount Mansfield in Vermont, USA, on August 28, 2010.

```
track = readgeotable('sample_mixed.gpx','Layer','track_points');
```

Write the log to a KML file by using the kmlwriteline function. The elevation values obtained by the GPS are relative to sea level.

```
filename = fullfile(kmlFolder,'GPS_Track_Log.kml');
lat = track.Shape.Latitude;
lon = track.Shape.Longitude;
alt = track.Elevation;
name = 'GPS Track Log';
kmlwriteline(filename,lat,lon,alt,'Name',name,'Color','k','Width',2, ...
    'AltitudeMode','relativeToSeaLevel');

Open the KML file.

openKML(filename)
Add filename to kmlFilenames.
kmlFilenames{end+1} = filename;
```

Example 10: Write Circles to KML File

This example writes circles as lines around London City Airport to a KML file. The example includes a LookAt virtual camera.

Assign latitude and longitude values for the center of the feature.

```
lat0 = 51.50487;
lon0 = .05235;
```

Assign azimuth to [] to compute a complete small circle. Use the WGS84 ellipsoid.

```
azimuth = [];
spheroid = wgs84Ellipsoid;
```

Compute small circles of 3000, 2000, and 1000 meter radius. Assign a color value of 'blue', 'green', and 'red' for each circle. Assign an elevation value of 100 meters (above ground) for each circle. Use a line geoshape vector to contain the data.

```
radius = 3000:-1000:1000;
colors = {'blue', 'green', 'red'};
elevation = 100;
circles = geoshape(0,0,'Name','','Color','','Elevation',elevation);
for k = 1:length(radius)
    [lat, lon] = scircle1(lat0,lon0,radius(k),azimuth,spheroid);
    circles(k).Latitude = lat;
    circles(k).Longitude = lon;
    circles(k).Name = [num2str(radius(k)) ' Meters'];
    circles(k).Color = colors{k};
    circles(k).Elevation = elevation;
end
```

Use a geopoint vector to define a LookAt virtual camera with a viewpoint from the east of the airport and aligned with the runway.

```
lat = 51.503169;
lon = 0.105478;
```

```
range = 3500;
heading = 270;
tilt = 60;
lookAt = geopoint(lat,lon,'Range',range,'Heading',heading,'Tilt',tilt);
Liso kmlurrite to write the geosphane vector containing the circles and associated di
```

Use kmlwrite to write the geoshape vector containing the circles and associated data to a KML file.

```
filename = fullfile(kmlFolder, 'Small_Circles.kml');
kmlwrite(filename, circles, 'AltitudeMode', 'relativeToGround', 'Width', 2, ...
    'Name', circles.Name, 'Color', circles.Color, 'LookAt', lookAt);
```

Open the KML file. Using Google Earth, the LookAt view point is set when clicking on either one of the 1000 Meters, 2000 Meters, or 3000 Meters strings in the Places list.

```
openKML(filename)
```

Add filename to kmlFilenames.

kmlFilenames{end+1} = filename;

Example 11: Write Circular Polygons to KML File

This example writes circular polygons around London City Airport to a KML file. It includes a LookAt virtual camera and uses the same data calculated in step 9.

Change the Geometry property value of the geoshape vector to 'polygon'. The polygons are drawn in the same order as the geoshape vector and are indexed from largest to smallest radii, thus each polygon will be visible in the browser.

```
circles.Geometry = 'polygon';
```

Change the elevation of each polygon.

```
circles.Elevation = 1000:1000:3000;
```

Use a geopoint vector to define a LookAt virtual camera with a viewpoint from the east of the airport, aligned with the runway, and with a view of all three polygons.

```
lat = 51.501587;
lon = 0.066147;
range = 13110;
heading = 270;
tilt = 60;
lookAt = geopoint(lat,lon,'Range',range,'Heading',heading,'Tilt',tilt);
```

Use kmlwrite to write the polygon geoshape vector containing the circular polygons and associated data to a KML file. Extrude the polygons to the ground. Set the polygon edge color to black and assign a face alpha value to provide visibility inside the polygon.

```
filename = fullfile(kmlFolder,'Small_Circle_Polygons.kml');
name = circles.Name;
color = circles.Color;
kmlwrite(filename,circles,'AltitudeMode','relativeToGround','Extrude',true, ...
    'Name',name,'FaceColor',color,'EdgeColor','k','FaceAlpha',.6,'LookAt',lookAt);
```

Open the KML file. Using Google Earth, the LookAt view point is set when clicking on either one of the 1000 Meters, 2000 Meters, or 3000 Meters strings in the Places list.

```
openKML(filename)
```

```
Add filename to kmlFilenames.

kmlFilenames{end+1} = filename;
```

Example 12: Write Polygon Data from Shapefile to KML file

This example writes polygon data from the shapefile called usastatelo.shp to a KML file. The polygon faces are set with a color appropriate for political regions. The polygon faces are set with an alpha value to provide visibility inside the polygon.

Example 13: Write Polygon Contours to KML File

This example contours a grid in a local coordinate system, returns the contours in a geographic system, and writes the polygon contours to a KML file.

Create a grid in a local system.

```
X = -150000:10000:150000;
Y = 0:10000:300000;
[xmesh, ymesh] = meshgrid(X/50000, (Y - 150000)/50000);
Z = 8 + peaks(xmesh, ymesh);
```

Define a local geodetic origin near Frankfurt, Germany and an ellipsoidal height.

```
lat0 = 50.108;
lon0 = 8.6732;
h0 = 100:
```

Define contour levels.

```
levels = 0:2:18;
```

Contour the grid and return the output in a polygon geoshape vector.

```
[~, contourPolygons] = geocontourxy(X,Y,Z,lat0,lon0,h0,'LevelList',levels);
```

Output the contours to a KML file. Set the faces with an alpha value. Set CutPolygons to false since the altitude values are not uniform. Clamp the polygons to the ground.

```
colors = parula(length(contourPolygons));
filename = fullfile(kmlFolder, 'Contour_Polygons.kml');
kmlwrite(filename, contourPolygons, 'FaceColor', colors, 'FaceAlpha', .6, ...
    'EdgeColor', 'k', 'CutPolygons', false, 'AltitudeMode', 'clampToGround')
```

```
Open the KML file.
openKML(filename)
Add filename to kmlFilenames.
kmlFilenames{end+1} = filename;
```

Example 14: Write Polygon with Inner Ring to KML File

This example constructs a polygon with an inner ring around the Eiffel Tower and writes the polygon to a KML file. The polygon's altitude is set to 500 meters above ground.

```
lat0 = 48.858288;
lon0 = 2.294548;
outerRadius = .02;
innerRadius = .01;
[lat1,lon1] = scircle1(lat0,lon0,outerRadius);
[lat2,lon2] = scircle1(lat0,lon0,innerRadius);
[lon2,lat2] = poly2ccw(lon2,lat2);
lat = [lat1; NaN; lat2];
lon = [lon1; NaN; lon2];
alt = 500;
filename = fullfile(kmlFolder,'EiffelTower.kml');
```

Export the polygon to a KML file. Set the edge color to black, the face color to cyan, and the face alpha value.

```
kmlwritepolygon(filename,lat,lon,alt,'EdgeColor','k','FaceColor','c', ...
'FaceAlpha',.5)

Open the KML file.
openKML(filename)
Add filename to kmlFilenames.
kmlFilenames{end+1} = filename;
```

Delete Generated KML Files

Optionally, delete the new KML files from your KML output folder.

```
if ~useApplication
    for k = 1:length(kmlFilenames)
        delete(kmlFilenames{k})
    end
end
```

Data Set Information

The data in worldcities.shp is from the Digital Chart of the World (DCW) browser layer, published by the U.S. National Geospatial-Intelligence Agency (NGA), formerly the National Imagery and Mapping Agency (NIMA). For more information about the data set, use the command type worldcities.txt.

The data in tsunamis.shp is from the Global Tsunami Database, U.S. National Geospatial Data Center (NGDC), National Oceanic and Atmospheric Administration (NOAA). For more information about the data set, use the command type tsunamis.txt.

The data in usastatelo.shp is based on data from the CIA World DataBank II and the U.S. Census Bureau site "State and County QuickFacts". For more information about the data set, use the command type usastatelo.txt. For an updated link to the U.S. Census Bureau site "State and County QuickFacts", see https://www.census.gov/quickfacts/fact/table/US/PST045221.

See Also

kmlwrite|kmlwritepolygon|kmlwriteline|kmlwritepoint

Export KML Files for Viewing in Earth Browsers

Keyhole Markup Language (KML) is an XML dialect for formatting 2-D and 3-D geodata for display in "Earth browsers," such as Google Earth™ mapping service, Google Maps™ mapping service, Google Mobile™ wireless service, and NASA WorldWind. Other Web browser applications, such as Yahoo!® Pipes, also support KML either by rendering or generating files. A KML file specifies a set of features (placemarks, images, polygons, 3-D models, textual descriptions, etc.) and how they are to be displayed in browsers and applications.

Each place must at least have an address or a longitude and a latitude. Places can also have textual descriptions, including hyperlinks. KML files can also specify display styles for markers, lines and polygons, and "camera view" parameters such as tilt, heading, and altitude. You can generate placemarks in KML files for individual points and sets of points that include attributes in table form. You can include HTML markups in these tables, with or without hyperlinks, but you cannot currently control the camera view of a placemark. (However, the users of an Earth browser can generally control their views of it).

Generate a Single Placemark Using kmlwritepoint

lat = 42.299827;

This example shows how to generate a placemark using kmlwritepoint by specifying the latitude and longitude that identifies a location. This example also specifies the icon used for the placemark and the text that appears in the balloon associated with the placemark.

```
lon = -71.350273;
description = sprintf('%s<br>%s</b><br>%s</b>', ...
     '3 Apple Hill Drive', 'Natick, MA. 01760', ...
    'https://www.mathworks.com');
name = 'The MathWorks, Inc.';
iconFilename = ..
    'https://www.mathworks.com/products/product listing/images/ml icon.gif';
iconScale = 1.0;
filename = 'MathWorks.kml';
kmlwritepoint(filename, lat, lon, ...
    'Description', description, 'Name', name, ...
    'Icon', iconFilename, 'IconScale', iconScale);
This code produces the following KML file.
<?xml version="1.0" encoding="utf-8"?>
<kml xmlns="http://www.opengis.net/kml/2.2">
   <Document>
      <name>MathWorks</name>
      <Placemark>
        <Snippet maxLines="0"> </Snippet>
        <description>3 Apple Hill Drive<br>Natick, MA. 01760</b>;
                     <br>https://www.mathworks.com</b>;
        </description>
        <name>The MathWorks, Inc.</name>
        <Style>
           .
<IconStvle>
              <Icon>
                <href>
                  https://www.mathworks.com/products/product_listing/images/ml_icon.gif
              </Icon>
              <scale>1</scale>
           </IconStyle>
        </Style>
        <Point>
           <coordinates>-71.350273.42.299827.0.0</coordinates>
        </Point>
     </Placemark>
   </Document>
</kml>
```

If you view this in an Earth Browser, notice that the text inside the placemark, "https://www.mathworks.com," was automatically rendered as a hyperlink. The Google Earth service also adds a link called "Directions". kmlwritepoint does not include location coordinates in placemarks. This is because it is easy for users to read out where a placemark is by mousing over it or by viewing its Properties dialog box.

Generate Placemarks from Addresses

This example shows how to generate a placemark using street addresses or more general addresses such as postal codes, city, state, or country names, instead of latitude and longitude information. If the viewing application is capable of looking up addresses, such placemarks can be displayed in appropriate, although possibly imprecise, locations. (Note that the Google Maps service does not support address-based placemarks.)

When you use addresses, kmlwrite creates an <address> element for each placemark rather than <point> elements containing <coordinates> elements. For example, here is code for kmlwrite that generates address-based placemarks for three cities in Australia from a cell array:

The generated KML file has the following structure and content:

```
<?xml version="1.0" encoding="utf-8"?>
<kml xmlns="http://www.opengis.net/kml/2.2">
   <Document>
      <name>Australian_Cities</name>
      <Placemark>
         <Snippet maxLines="0"> </Snippet>
         <description> </description>
         <name>Perth, Australia</name>
         <address>Perth, Australia</address>
      </Placemark>
      <Placemark>
         <Snippet maxLines="0"> </Snippet>
         <description> </description>
         <name>Melbourne. Australia</name>
         <address>Melbourne, Australia</address>
      </Placemark>
      <Placemark>
         <Snippet maxLines="0"> </Snippet>
         <description> </description>
         <name>Sydney, Australia</name>
         <address>Sydney, Australia</address>
      </Placemark>
   </Document>
</kml>
```

Export Point Geostructs to Placemarks

This example shows how to read data from shapefiles and generate a KML file that identifies all or selected attributes, which you can then view in an earth browser such as Google Earth. It also shows how to customize placemark icons and vary them according to attribute values.

The Mapping Toolbox tsunamis shapefiles contain a database of 162 tsunami (tidal wave) events reported between 1950 and 2006, described as point locations with 21 variables (including 18 attributes). You can type out the metadata file tsunamis.txt to see the definitions of all the data fields. The steps below select some of these from the shapefiles and display them as tables in exported KML placemarks.

1 Read the tsunami shapefiles, selecting certain attributes.

There are several ways to select attributes from shapefiles. One is to pass shaperead a cell array of attribute names in the Attributes parameter. For example, you might just want to map the maximum wave height, the suspected cause, and also show the year, location and country for each event. Set up a cell array with the corresponding attribute field names as follows, remembering that field names are case-sensitive.

```
attrs = {'Max_Height','Cause','Year','Location','Country'};
```

Since the data file uses latitude and longitude coordinates, you need to specify 'UseGeoCoords', true to ensure that shaperead returns a geostruct (having Lat and Lon fields).

Look at the first record in the tsunamis geostruct returned by shaperead.

tsunamis(1)

```
Geometry: 'Point'
Lon: 128.3000
Lat: -3.8000
Max_Height: 2.8000
Cause: 'Earthquake'
Year: 1950
Location: 'JAVA TRENCH, INDONESIA'
Country: 'INDONESIA'
```

2 Export the tsunami data to a KML file with kmlwrite

By default, kmlwrite outputs all attribute data in a geostruct to a KML formatted file as an HTML table containing unstyled text. When you view it, the Google Earth program supplies a default marker.

```
kmlfilename = 'tsunami1.kml';
kmlwritepoint(kmlfilename,tsunamis(1).Lat,tsunamis(1).Lon);
```

View the placemarks in an earth browser. For example, you can view KML files with the Google Earth browser, which must be installed on your computer.

For Windows, use the winopen function:

```
winopen(filename)
```

For Linux, if the file name is a partial path, use the following commands:

```
cmd = 'googleearth ';
fullfilename = fullfile(pwd, filename);
system([cmd fullfilename])
```

For Mac, if the file name is a partial path, use the following commands:

```
cmd = 'open -a Google\ Earth '
fullfilename = fullfile(pwd, filename);
system([cmd fullfilename])
```

4 Customize the placemark contents

To customize the HTML table in the placemark, use the makeattribspec function. Create an attribute spec for the tsunamis geostruct and inspect it.

```
attribspec = makeattribspec(tsunamis)
attribspec =
    Max_Height: [1x1 struct]
          Cause: [1x1 struct]
          Year: [1x1 struct]
          Location: [1x1 struct]
          Country: [1x1 struct]
```

Format the label for Max_Height as bold text, give units information about Max_Height, and also set the other attribute labels in bold.

```
attribspec.Max_Height.AttributeLabel = '<b>Maximum Height</b>';
attribspec.Max_Height.Format = '%.1f Meters';
attribspec.Cause.AttributeLabel = '<b>Cause</b>';
attribspec.Year.AttributeLabel = '<b>Year</b>';
attribspec.Year.Format = '%.0f';
attribspec.Location.AttributeLabel = '<b>Location</b>';
attribspec.Country.AttributeLabel = '<b>Country</b>';
```

When you use the attribute spec, all the attributes it lists are included in the placemarks generated by kmlwrite unless you remove them from the spec manually (e.g., with rmfield).

5 Customize the placemark icon

You can specify your own icon using kmlwrite to use instead of the default pushpin symbol. The black-and-white bullseye icon used here is specified as URL for an icon in the Google KML library.

```
iconname = ...
   'http://maps.google.com/mapfiles/kml/shapes/placemark_circle.png';
kmlwritepoint(kmlfilename,tsunamis(1).Lat,tsunamis(1).Lon, ...
   'Description',attribspec,'Name',{tsunamis(1).Location}, ...
   'Icon',iconname,'IconScale',2);
```

6 Vary placemark size by tsunami height

To vary the size of placemark icons, specify an icon file and a scaling factor for every observation as vectors of names (all the same) and scale factors (all computed individually) when writing a KML file. Scale the width and height of the markers to the log of Max_Height. Scaling factors for point icons are data-dependent and can take some experimenting with to get right.

Select Shapefile Data to Read

The shaperead function provides you with a powerful method, called a *selector*, to select only the data fields and items you want to import from shapefiles.

A selector is a cell array with two or more elements. The first element is a handle to a predicate function (a function with a single output argument of type logical). Each remaining element is a character vector indicating the name of an attribute.

For a given feature, shaperead supplies the values of the attributes listed to the predicate function to help determine whether to include the feature in its output. The feature is excluded if the predicate returns false. The converse is not necessarily true: a feature for which the predicate returns true may be excluded for other reasons when the selector is used in combination with the bounding box or record number options.

The following examples are arranged in order of increasing sophistication. Although they use MATLAB function handles, anonymous functions, and nested functions, you do not need to be familiar with these features to use the selectors for shaperead.

Example 1: Predicate Function in Separate File

Define the predicate function in a separate file. (Prior to Release 14, this was the only option available.) Create a file named roadfilter.m, with the following contents:

2 You can then call shaperead like this:

```
roadselector = {@roadfilter, 'CLASS', 'LENGTH'}
roadselector =
    @roadfilter
                    'CLASS'
                                'LENGTH'
s = shaperead('concord roads.shp', 'Selector', roadselector)
s =
115x1 struct array with fields:
    Geometry
    BoundingBox
    Χ
    STREETNAME
    RT NUMBER
    CLASS
    ADMIN TYPE
    LENGTH
or, in a slightly more compact fashion, like this:
s = shaperead('concord_roads.shp',...
```

'Selector', {@roadfilter, 'CLASS', 'LENGTH'})

```
s =
115x1 struct array with fields:
   Geometry
   BoundingBox
   X
   Y
   STREETNAME
   RT_NUMBER
   CLASS
   ADMIN_TYPE
   LENGTH
```

Prior to Version 7 of the Mapping Toolbox software, putting the selector in a file or local function of its own was the only way to work with a selector.

Note that if the call to shaperead took place within a function, then roadfilter could be defined in a local function thereof rather than in a file of its own.

Example 2: Predicate as Function Handle

As a simple variation on the previous example, you could assign a function handle, roadfilterfcn, and use it in the selector:

Example 3: Predicate as Anonymous Function

Having to define predicate functions in files of their own, or even as local functions, may sometimes be awkward. Anonymous functions allow the predicate function to be defined right where it is needed. For example:

```
roadfilterfcn = ...
  @(roadclass, roadlength) (roadclass >= 4) && ...
  (roadlength >= 200)

roadfilterfcn =
   @(roadclass, roadlength) (roadclass >= 4) ...
        && (roadlength >= 200)

s = shaperead('concord_roads.shp','Selector', ...
```

```
{roadfilterfcn, 'CLASS', 'LENGTH'})
s =
115x1 struct array with fields:
    Geometry
    BoundingBox
    X
    Y
    STREETNAME
    RT_NUMBER
    CLASS
    ADMIN_TYPE
    LENGTH
```

Example 4: Predicate (Anonymous Function) Defined Within Cell Array

There is actually no need to introduce a function handle variable when defining the predicate as an anonymous function. Instead, you can place the whole expression within the selector cell array itself, resulting in somewhat more compact code. This pattern is used in many examples throughout the Mapping Toolbox documentation and function help.

```
s = shaperead('concord_roads.shp', 'Selector', ...
    {@(roadclass, roadlength)...
    (roadclass >= 4) && (roadlength >= 200),...
    'CLASS', 'LENGTH'})

s =
115x1 struct array with fields:
    Geometry
    BoundingBox
    X
    Y
    STREETNAME
    RT_NUMBER
    CLASS
    ADMIN_TYPE
    LENGTH
```

Example 5: Parametrizing the Selector; Predicate as Nested Function

In the previous patterns, the predicate involves two hard-coded parameters (called minimumClass and minimumLength in roadfilter.m), as well as the roadclass and roadlength input variables. If you use any of these patterns in a program, you need to decide on minimum cut-off values for roadclass and roadlength at the time you write the program. But suppose that you wanted to wait and decide on parameters like minimumClass and minimumLength at run time?

Fortunately, nested functions provide the additional power that you need to do this; they allow you to utilize workspace variables in as parameters, rather than requiring that the parameters be hard-coded as constants within the predicate function. In the following example, the workspace variables minimumClass and minimumLength could have been assigned through a variety of computations whose results were unknown until run-time, yet their values can be made available within the predicate as long as it is defined as a nested function. In this example the nested function is wrapped in a file called constructroadselector.m, which returns a complete selector: a handle to the predicate (named nestedroadfilter) and the two attribute names:

```
function roadselector = ...
     constructroadselector(minimumClass, minimumLength)
 roadselector = {@nestedroadfilter, 'CLASS', 'LENGTH'};
     function result = nestedroadfilter(roadclass, roadlength)
         result = (roadclass >= minimumClass) && ...
                  (roadlength >= minimumLength);
     end
end
The following four lines show how to use constructroadselector:
minimumClass = 4;
                      % Could be run-time dependent
minimumLength = 200; % Could be run-time dependent
roadselector = constructroadselector(...
   minimumClass, minimumLength);
s = shaperead('concord_roads.shp', 'Selector', roadselector)
s =
115x1 struct array with fields:
   Geometry
   BoundingBox
   Χ
   Υ
    STREETNAME
   RT NUMBER
   CLASS
   ADMIN TYPE
   LENGTH
```

Export Images and Raster Grids to GeoTIFF

This example shows how to write data referenced to standard geographic and projected coordinate systems to GeoTIFF files, using geotiffwrite. The Tagged-Image File Format (TIFF) has emerged as a popular format to store raster data. The GeoTIFF specification defines a set of TIFF tags that describe "Cartographic" information associated with the TIFF raster data. Using these tags, geolocated imagery or raster grids with coordinates referenced to a Geographic Coordinate System (latitude and longitude) or a (planar) Projected Coordinate System can be stored in a GeoTIFF file.

Setup: Define a Data Folder and File Name Utility Function

This example creates several temporary GeoTIFF files and uses the variable datadir to denote their location. The value used here is determined by the output of the tempdir command, but you could easily customize this. The contents of datadir are deleted at the end of the example.

```
datadir = fullfile(tempdir, 'datadir');
if ~exist(datadir, 'dir')
   mkdir(datadir)
end
```

Define an anonymous function to prepend datadir to the input file name:

```
datafile = @(filename)fullfile(datadir, filename);
```

Example 1: Write an Image Referenced to Geographic Coordinates

Write an image referenced to WGS84 geographic coordinates to a GeoTIFF file. The original image (boston_ovr.jpg) is stored in JPEG format, with referencing information external to the image file, in the "world file" (boston_ovr.jgw). The image provides a low resolution "overview" of Boston, Massachusetts, and the surrounding area.

Read the image from the JPEG file.

```
basename = 'boston_ovr';
imagefile = [basename '.jpg'];
Al = imread(imagefile);

Obtain a referencing object from the world file.
worldfile = getworldfilename(imagefile);
Rl = worldfileread(worldfile, 'geographic', size(Al));


Write the image to a GeoTIFF file.
filename1 = datafile([basename '.tif']);
geotiffwrite(filename1,A1,R1)

Return information about the file as a RasterInfo object. Note that the value of CoordinateReferenceSystem is a geographic coordinate reference system object.
infol = georasterinfo(filename1);
infol.CoordinateReferenceSystem
```

Re-import the new GeoTIFF file and display the Boston overview image, correctly located, on a map.

```
figure
usamap(R1.LatitudeLimits,R1.LongitudeLimits)
setm(gca,'PLabelLocation',0.05,'PlabelRound',-2,'PlineLocation',0.05)
geoshow(filename1)
title('Boston Overview')
```

Boston Overview




Example 2: Write a Data Grid Referenced to Geographic Coordinates

Load elevation raster data and a geographic cells reference object. Write the data grid to a GeoTIFF file.

```
load topo60c
Z2 = topo60c;
R2 = topo60cR;
filename2 = datafile('topo60c.tif');
geotiffwrite(filename2,Z2,R2)
```

The values in the data grid range from -7473 to 5731. Display the grid as a texture-mapped surface rather than as an intensity image.

```
figure
worldmap world
gridm off
setm(gca,'MLabelParallel',-90,'MLabelLocation',90)
tmap = geoshow(filename2,'DisplayType','texturemap');
demcmap(tmap.CData)
title('Elevation Data Grid')
```



Example 3: Change Data Organization of GeoTIFF Files

When you write data using geotiffwrite or read data using readgeoraster, the columns of the data grid start from north and the rows start from west. For example, the input data from topo60c.mat starts from south, but the output data from topo60c.tif starts from north.

```
R2.ColumnsStartFrom
[Z3,R3] = readgeoraster(filename2);
R3.ColumnsStartFrom

ans =
    'south'
```

```
'north'
```

Therefore, the input data and data in the GeoTIFF file is flipped.

```
isequal(Z2,flipud(Z3))
ans =
  logical
  1
```

If you need the data in your workspace to match again, then flip the Z values and set the referencing object such that the columns start from the south:

```
R3.ColumnsStartFrom = 'south';
Z3 = flipud(Z3);
isequal(Z2,Z3)

ans =
  logical
  1
```

The data in the GeoTIFF file is encoded with positive scale values. Therefore, when you view the file with ordinary TIFF-viewing software, the northern edge of the data set is at the top. To make the data layout in the output file match the data layout of the input, you can construct a Tiff object and use it to reset some of the tags and the image data.

```
t = Tiff(filename2,'r+');
pixelScale = getTag(t,'ModelPixelScaleTag');
pixelScale(2) = -pixelScale(2);
setTag(t,'ModelPixelScaleTag',pixelScale);

tiepoint = getTag(t,'ModelTiepointTag');
tiepoint(5) = intrinsicToGeographic(R2,0.5,0.5);
setTag(t,'ModelTiepointTag',tiepoint);
setTag(t,'Compression', Tiff.Compression.None)
write(t,Z2);
rewriteDirectory(t)
close(t)
```

Verify the referencing object and data grid from the input data match the output data file. To do this, read the Tiff image and create a reference object. Then, compare the grids.

```
t = Tiff(filename2);
Atiff = read(t);
```

```
close(t)
Rtiff = georefcells(R2.LatitudeLimits,R2.LongitudeLimits,size(Atiff));
isequal(Z2,Atiff)
isequal(R2,Rtiff)

ans =
  logical
  1

ans =
  logical
  1
```

Example 4: Write an Image Referenced to a Projected Coordinate System

Write the Concord orthophotos to a single GeoTIFF file. The two adjacent (west-to-east) georeferenced grayscale (panchromatic) orthophotos cover part of Concord, Massachusetts, USA. The concord_ortho.txt file indicates that the data are referenced to the Massachusetts Mainland (NAD83) State Plane Projected Coordinate System. Units are meters. This corresponds to the GeoTIFF code number 26986 as noted in the GeoTIFF specification at http://geotiff.maptools.org/spec/geotiff6.html#6.3.3.1 under PCS NAD83 Massachusetts.

Read the two orthophotos.


```
[X west,R west] = readgeoraster('concord ortho w.tif');
[X east,R east] = readgeoraster('concord ortho e.tif');
Combine the images and reference objects.
X4 = [X west X east];
R4 = R_{west};
R4.XWorldLimits = [R west.XWorldLimits(1) R east.XWorldLimits(2)];
R4.RasterSize = size(X4);
Write the data to a GeoTIFF file. Use the code number, 26986, indicating the
PCS NAD83 Massachusetts Projected Coordinate System.
coordRefSysCode = 26986;
filename4 = datafile('concord ortho.tif'):
geotiffwrite(filename4,X4,R4,'CoordRefSysCode',coordRefSysCode)
Return information about the file as a RasterInfo object. Note that the value of
CoordinateReferenceSystem is a projected coordinate reference system object.
info4 = georasterinfo(filename4);
info4.CoordinateReferenceSystem
ans =
```

```
projcrs with properties:
```

```
Name: "NAD83 / Massachusetts Mainland"
GeographicCRS: [1×1 geocrs]
ProjectionMethod: "Lambert Conic Conformal (2SP)"
LengthUnit: "meter"
ProjectionParameters: [1×1 map.crs.ProjectionParameters]
```

Display the combined Concord orthophotos.

```
figure
mapshow(filename4)
title('Combined Orthophotos')
xlabel('MA Mainland State Plane easting, meters')
ylabel('MA Mainland State Plane northing, meters')
```



Example 5: Write a Cropped Image from a GeoTIFF File

Write a subset of a GeoTIFF file to a new GeoTIFF file.

Read the RGB image and referencing information from the boston.tif GeoTIFF file.

```
[A5,R5] = readgeoraster('boston.tif');
```

Crop the image.


```
xlimits = [ 764318   767677];
ylimits = [2951122 2954482];
[A5crop,R5crop] = mapcrop(A5,R5,xlimits,ylimits);
```

Write the cropped image to a GeoTIFF file. Use the GeoKeyDirectoryTag from the original GeoTIFF file.

```
info5 = geotiffinfo('boston.tif');
filename5 = datafile('boston_subimage.tif');
geotiffwrite(filename5,A5crop,R5crop, ...
   'GeoKeyDirectoryTag',info5.GeoTIFFTags.GeoKeyDirectoryTag)
```

Display the GeoTIFF file containing the cropped image.

```
figure
mapshow(filename5)
title('Fenway Park - Cropped Image from GeoTIFF File')
xlabel('MA Mainland State Plane easting, survey feet')
ylabel('MA Mainland State Plane northing, survey feet')
```



Example 6: Write Elevation Data to GeoTIFF File

Write elevation data for an area around South Boulder Peak in Colorado to a GeoTIFF file.

```
elevFilename = 'n39_w106_3arc_v2.dt1';
```

Read the DEM from the file. To plot the data using geoshow, the data must be of type single or double. Specify the data type for the raster using the 'OutputType' name-value pair.

```
[Z6,R6] = readgeoraster(elevFilename, 'OutputType', 'double');
```

Create a structure to hold the GeoKeyDirectoryTag information.

```
key = struct( ...
    'GTModelTypeGeoKey',[], ...
    'GTRasterTypeGeoKey',[], ...
'GeographicTypeGeoKey',[]);
```


Indicate the data is in a geographic coordinate system by specifying the GTModelTypeGeoKey field as 2. Indicate that the reference object uses postings (rather than cells) by specifying the GTRasterTypeGeoKey field as 2. Indicate the data is referenced to a geographic coordinate reference system by specifying the GeographicTypeGeoKey field as 4326.

```
key.GTModelTypeGeoKey = 2;
key.GTRasterTypeGeoKey = 2;
key.GeographicTypeGeoKey = 4326;
Write the elevation data to a GeoTIFF file.
filename6 = datafile('southboulder.tif');
geotiffwrite(filename6,Z6,R6,'GeoKeyDirectoryTag',key)
```

Verify the data has been written to a file by displaying it. First, import vector data that represents the state boundary of Colorado using readgeotable. Then, display the boundary and GeoTIFF file.

```
GT = readgeotable('usastatelo.shp');
row = GT.Name == 'Colorado';
colorado = GT(row,:);

figure
usamap 'Colorado'
hold on
geoshow(colorado,'FaceColor','none')
g = geoshow(filename6,'DisplayType','mesh');
demcmap(g.ZData)
title('South Boulder Peak Elevation')
```



Example 7: Write Non-Image Data to a TIFF File

If you are working with a data grid that is class double with values that range outside the limits required of a floating point intensity image (0 <= data <= 1), and if you store the data in a TIFF file using imwrite, then your data will be truncated to the interval [0,1], scaled, and converted to uint8. Obviously it is possible for some or even all of the information in the original data to be lost. To avoid these problems, and preserve the numeric class and range of your data grid, use geotiffwrite to write the data.

Create sample Z data.

```
n = 512;
Z7 = peaks(n);
```

Create a referencing object to reference the rows and columns to X and Y.

```
R7 = maprasterref('RasterSize',[n n],'ColumnsStartFrom','north');
R7.XWorldLimits = R7.XIntrinsicLimits;
R7.YWorldLimits = R7.YIntrinsicLimits;
```

Create a structure to hold the GeoKeyDirectoryTag information. Set the model type to 1 indicating Projected Coordinate System (PCS).

```
key.GTModelTypeGeoKey = 1;
```

Set the raster type to 1 indicating PixelIsArea (cells).

```
key.GTRasterTypeGeoKey = 1;
```

Indicate a user-defined Projected Coordinate System by using a value of 32767.

```
key.ProjectedCSTypeGeoKey = 32767;
```

Write the data to a GeoTIFF file with geotiffwrite. For comparison, write a second file using imwrite.

```
filename_geotiff = datafile('zdata_geotiff.tif');
filename_tiff = datafile('zdata_tiff.tif');
geotiffwrite(filename_geotiff,Z7,R7,'GeoKeyDirectoryTag',key)
imwrite(Z7, filename_tiff);
```


When you read the file using imread the data values and class type are preserved. You can see that the data values in the TIFF file are not preserved.

```
geoZ = imread(filename_geotiff);
tiffZ = imread(filename_tiff);
fprintf('Class type of Z: %s\n', class(Z7))
fprintf('Class type of data in GeoTIFF file: %s\n', class(geoZ))
fprintf('Class type of data in TIFF file: %s\n', class(tiffZ))
fprintf('Does data in GeoTIFF file equal Z: %d\n', isequal(geoZ, Z7))
fprintf('Does data in TIFF file equal Z: %d\n', isequal(tiffZ, Z7))

Class type of Z: double
Class type of data in GeoTIFF file: double
Class type of data in TIFF file: uint8
Does data in GeoTIFF file equal Z: 1
Does data in TIFF file equal Z: 0
```

You can view the data grid using mapshow.

```
figure
mapshow(filename_geotiff,'DisplayType','texturemap')
title('Peaks - Stored in GeoTIFF File')
```



Example 8: Modify an Existing File While Preserving Meta Information

You may want to modify an existing file, but preserve most, if not all, of the meta information in the TIFF tags. This example converts the RGB image from the boston.tif file into an indexed image and writes the new data to an indexed GeoTIFF file. The TIFF meta-information, with the exception of the values of the BitDepth, BitsPerSample, and PhotometricInterpretation tags, is preserved.

Read the image from the boston.tif GeoTIFF file.

```
[A8,R8] = readgeoraster('boston.tif');
```

Use the MATLAB function, rgb2ind, to convert the RGB image to an indexed image X using minimum variance quantization.

```
[X8, cmap] = rgb2ind(A8, 65536);
```

Obtain the TIFF tag information using imfinfo.

```
info8 = imfinfo('boston.tif');
```

Create a TIFF tags structure to preserve selected information from the info structure.

```
tags = struct( ...
    'Compression', info8.Compression, ...
    'RowsPerStrip', info8.RowsPerStrip, ...
    'XResolution', info8.XResolution, ...
    'YResolution', info8.YResolution, ...
    'ImageDescription', info8.ImageDescription, ...
```

```
'DateTime', info8.DateTime, ...
'Copyright', info8.Copyright, ...
'Orientation', info8.Orientation);
```

The values for the PlanarConfiguration and ResolutionUnit tags must be numeric rather than string valued, as returned by imfinfo. You can set these tags by using the constant properties from the Tiff class. For example, here are the possible values for the PlanarConfiguration constant property:


Tiff.PlanarConfiguration

mapshow(filename8)

title('Boston - Indexed Image')

xlabel('MA Mainland State Plane easting, survey feet')
ylabel('MA Mainland State Plane northing, survey feet')

```
ans =
  struct with fields:
      Chunky: 1
    Separate: 2
Use the string value from the info structure to obtain the desired value.
tags.PlanarConfiguration = ...
    Tiff.PlanarConfiguration.(info8.PlanarConfiguration);
Set the ResolutionUnit value in the same manner.
tags.ResolutionUnit = Tiff.ResolutionUnit.(info8.ResolutionUnit);
The Software tag is not set in the boston.tif file. However, geotiffwrite will set the Software
tag by default. To preserve the information, set the value to the empty string which prevents the tag
from being written to the file.
tags.Software = '';
Copy the GeoTIFF information from boston.tif.
geoinfo = geotiffinfo('boston.tif');
key = geoinfo.GeoTIFFTags.GeoKeyDirectoryTag;
Write to the GeoTIFF file.
filename8 = datafile('boston indexed.tif');
qeotiffwrite(filename8,X8,cmap,R8,'GeoKeyDirectoryTag',key,'TiffTags',tags)
View the indexed image.
figure
```



Compare the information in the structures that should be equal by printing a table of the values.

```
info rgb = imfinfo('boston.tif');
info indexed = imfinfo(filename8);
tagNames = fieldnames(tags);
tagNames(strcmpi('Software', tagNames)) = [];
names = [{'Height' 'Width'}, tagNames'];
spacing = 2;
fieldnameLength = max(cellfun(@length, names)) + spacing;
formatSpec = ['%-' int2str(fieldnameLength) 's'];
fprintf([formatSpec formatSpec '\n'], ...
    'Fieldname', 'RGB Information', 'Indexed Information')
fprintf([formatSpec formatSpec '\n'], ...
    '----', '-----
for k = 1:length(names)
    fprintf([formatSpec formatSpec '\n'], ...
       names{k}, ...
       num2str(info rgb.(names{k})), ...
       num2str(info_indexed.(names{k})))
end
                    RGB Information
                                         Indexed Information
Fieldname
Height
                    2881
                                         2881
Width
                    4481
                                         4481
```

Compare the information that should be different, since you converted an RGB image to an indexed image, by printing a table of values.

```
names = {'FileSize', 'ColorType', 'BitDepth', ...
    'BitsPerSample', 'PhotometricInterpretation'};
fieldnameLength = max(cellfun(@length, names)) + spacing;
formatSpec = ['%-' int2str(fieldnameLength) 's'];
formatSpec2 = '%-17s';
fprintf(['\n' formatSpec formatSpec2 formatSpec2 '\n'], ...
    'Fieldname', 'RGB Information', 'Indexed Information')
fprintf([formatSpec formatSpec2 '\n'], ...
    '----', '-----')
for k = 1:length(names)
   fprintf([formatSpec formatSpec2 '\n'], ...
       names{k}, ...
       num2str(info_rgb.(names{k})), ...
       num2str(info indexed.(names{k})))
end
Fieldname
                        RGB Information Indexed Information
                                   27925078
indexed
FileSize
                       38729900
ColorType
                       truecolor
BitDepth
                        24
                                       16
                        8 8 8
BitsPerSample
                                       16
PhotometricInterpretation RGB
                                       RGB Palette
```

Cleanup: Remove Data Folder

Remove the temporary folder and data files.

```
rmdir(datadir, 's')
```

Data Set Information

The files boston.tif and boston_ovr.jpg include materials copyrighted by GeoEye, all rights reserved. GeoEye was merged into the DigitalGlobe corporation on January 29th, 2013. For more information about the data sets, use the commands type boston.txt and type boston ovr.txt.

The files <code>concord_orthow_w.tif</code> and <code>concord_ortho_e.tif</code> are derived using orthophoto tiles from the Bureau of Geographic Information (MassGIS), Commonwealth of Massachusetts, Executive Office of Technology and Security Services. For more information about the data sets, use the <code>command type concord_ortho.txt</code>. For an updated link to the data provided by MassGIS, see https://www.mass.gov/info-details/massgis-data-layers.

The DTED file $n39_w106_3arc_v2.dt1$ is courtesy of the US Geological Survey.

See Also

geotiffwrite|worldfileread|getworldfilename|geotiffinfo

Create, Process, and Export Digital Surface Model from Lidar Data

This example shows how to process aerial lidar data received from an airborne lidar system into a GeoTIFF file. Import a LAZ file containing aerial lidar data, create a spatially referenced digital surface model (DSM) from the data, crop the DSM to an area of interest, and export the cropped DSM to a GeoTIFF file.


When you export a DSM to a GeoTIFF file, you also export the projected coordinate reference system (CRS) for the data. Projected CRSs associate *x*- and *y*-coordinates to locations on Earth. Specifying the projected CRS is important when creating a model because the same coordinates in different projected CRSs can refer to different locations.

Read Aerial Lidar Data

Read 3-D point cloud data for an area near Tuscaloosa, Alabama from a LAZ file [1 on page 2-125]. The area includes roads, trees, and buildings.

```
lazFileName = fullfile(toolboxdir("lidar"),"lidardata","las","aerialLidarData.laz");
lasReader = lasFileReader(lazFileName);
ptCloud = readPointCloud(lasReader);
Display the data.
figure
```

figure
pcshow(ptCloud.Location)



Create DSM

A DSM includes the elevations of ground points, the elevations of natural features such as trees, and the elevations of artificial features such as buildings. Create a DSM from the point cloud data by using the pc2dem function. Use the maximum point from each element of the point cloud, which corresponds to the first return pulse of the lidar data, by specifying the CornerFillMethod as "max". The function returns an array of elevation values and the x- and y-limits of the data.

```
gridRes = 1;
[Z,xlimits,ylimits] = pc2dem(ptCloud,gridRes,CornerFillMethod="max");
```

Spatially Reference DSM

Spatially reference the DSM by creating a map reference object.

```
RasterExtentInWorldX: 401
RasterExtentInWorldY: 284
   XIntrinsicLimits: [1 402]
   YIntrinsicLimits: [1 285]
   TransformationType: 'rectilinear'
CoordinateSystemType: 'planar'
   ProjectedCRS: []
```

The reference object contains information such as the limits, the distance between the points, and the directions of the columns and rows. By default, the reference object assumes that columns start from the south and rows start from the west. These default values are consistent with the output of the pc2dem function, which creates the elevation array such that the first element represents the southwesternmost point.


The ProjectedCRS property of the reference object is empty, which means the DSM is not associated with a projected CRS. Read the CRS from the LAZ file and update the ProjectedCRS property.

A projected CRS consists of a geographic CRS and several parameters that are used to transform coordinates to and from the geographic CRS. A geographic CRS consists of a datum (including a reference ellipsoid), a prime meridian, and an angular unit of measurement. View the geographic CRS and its reference ellipsoid.

```
SemiminorAxis: 6356752.31414036
InverseFlattening: 298.257222101
Eccentricity: 0.0818191910428158
and additional properties:
Flattening
ThirdFlattening
MeanRadius
SurfaceArea
Volume
```

Display the spatially referenced DSM as an overhead surface by using the mapshow function.

```
figure
mapshow(Z,R,DisplayType="surface")
axis image
title("Digital Surface Model (DSM) from Aerial Lidar Data")
```



Crop DSM to Region of Interest

Represent the DSM region as a polygon by using a mappolyshape object. Update the ProjectedCRS property to match the CRS of the DSM.

```
bboxx = xlimits([1 1 2 2 1]);
bboxy = ylimits([1 2 2 1 1]);
```

```
bboxshape = mappolyshape(bboxx,bboxy);
bboxshape.ProjectedCRS = p;
```

View the region using satellite imagery. You can visually confirm that the satellite imagery aligns with the DSM visualization created using the mapshow function.

```
regioncolors = lines(2);
geoplot(bboxshape, ...
    EdgeColor=regioncolors(1,:), ...
    FaceAlpha=0.2, ...
    LineWidth=2, ...
    DisplayName="Aerial Lidar Data Region")
hold on
geobasemap satellite
legend
```



Select and display a region of interest. To use a predefined region that is bounded by roads on the east, north, and west, specify interactivelySelectPoints as false. Alternatively, you can interactively select four points that define a region by specifying interactivelySelectPoints as true.

```
interactivelySelectPoints = false;
if interactivelySelectPoints
    [cropbboxlat,cropbboxlon] = ginput(4); %#ok<UNRCH>
else
    cropbboxlat = [33.2571550; 33.2551982; 33.2551982; 33.2571125];
    cropbboxlon = [-87.7530648; -87.7530139; -87.7509086; -87.7509086];
```

```
end
cropbboxlat(end+1) = cropbboxlat(1);
cropbboxlon(end+1) = cropbboxlon(1);
cropbboxshape = geopolyshape(cropbboxlat,cropbboxlon);
geoplot(cropbboxshape, ...
    EdgeColor=regioncolors(2,:), ...
    FaceAlpha=0.2, ...
    LineWidth=2, ...
    DisplayName="Selected Region of Interest")
```



Transform the latitude and longitude limit coordinates for the region to x- and y-limit coordinates. The geographic CRS underlying the satellite basemap is WGS84, while the geographic CRS underlying the DSM data is NAD83. NAD83 and WGS84 are similar, but not identical. As a result, there can be discrepancies in coordinates between the satellite imagery and DSM.

```
[cropbboxx,cropbboxy] = projfwd(p,cropbboxlat(:),cropbboxlon(:));
```

Create the crop limits by finding the bounds of the *x*- and *y*-coordinates.

```
[cropxlimmin,cropxlimmax] = bounds(cropbboxx);
cropxlimits = [cropxlimmin cropxlimmax];
[cropylimmin,cropylimmax] = bounds(cropbboxy);
cropylimits = [cropylimmin cropylimmax];
```

Create a new spatially referenced DSM that contains data within the region of interest.

```
[Zcrop,Rcrop] = mapcrop(Z,R,cropxlimits,cropylimits);
```

Export DSM to GeoTIFF File

Write the cropped DSM to a GeoTIFF file called lidardsm.tif. Specify the projected CRS by using the CoordRefSysCode argument. The metadata for the LAZ file [1 on page 2-125] indicates the projected CRS is UTM Zone 16N, specified by EPSG authority code 26916.

```
datafile = "lidardsm.tif";
epsgCode = 26916;
geotiffwrite(datafile,Zcrop,Rcrop,CoordRefSysCode=epsgCode)
```

You can also find the authority code by displaying the well-known text (WKT) string for the projected CRS. For this WKT, the authority code is in the last line.


```
wktstring(p, "Format", "formatted")
ans =
    "PROJCRS["NAD83 / UTM zone 16N",
         BASEGEOGCRS["NAD83",
             DATUM["North American Datum 1983",
                 ELLIPSOID["GRS 1980",6378137,298.257222101,
                     LENGTHUNIT["metre",1]]],
             PRIMEM["Greenwich", 0,
                 ANGLEUNIT["degree", 0.0174532925199433]],
             ID["EPSG",4269]],
         CONVERSION["UTM zone 16N",
             METHOD["Transverse Mercator",
                 ID["EPSG",9807]],
             PARAMETER["Latitude of natural origin",0,
                 ANGLEUNIT["degree", 0.0174532925199433],
                 ID["EPSG",8801]],
             PARAMETER["Longitude of natural origin", -87,
                 ANGLEUNIT["degree", 0.0174532925199433],
                 ID["EPSG",8802]],
             PARAMETER["Scale factor at natural origin", 0.9996,
                 SCALEUNIT["unity",1],
                 ID["EPSG",8805]],
             PARAMETER["False easting",500000,
                 LENGTHUNIT["metre",1],
                 ID["EPSG",8806]],
             PARAMETER["False northing",0,
                 LENGTHUNIT["metre",1],
                 ID["EPSG",8807]]],
         CS[Cartesian, 2],
             AXIS["easting", east,
                 ORDER[1],
                 LENGTHUNIT["metre",1]],
             AXIS["northing", north,
                 ORDER[2],
                 LENGTHUNIT["metre",1]],
         ID["EPSG",26916]]"
```

One way to validate the GeoTIFF file is to return information about the file as a RasterInfo object. For example, verify that the projected CRS is in the file by querying the CoordinateReferenceSystem property of the RasterInfo object.

```
info = georasterinfo(datafile);
info.CoordinateReferenceSystem
```

Another way to validate the GeoTIFF file is by displaying it. Read the new DSM as an array and a reference object by using the readgeoraster function. Then, display the DSM.

```
[Z2,R2] = readgeoraster(datafile);
figure
mapshow(Z2,R2,DisplayType="surface")
axis image
title("Cropped DSM from Aerial Lidar Data")
```



You can use the GeoTIFF file in other applications that import GIS data. For example, RoadRunner enables you to add elevation data from GeoTIFF files to scenes.

References

[1] Open Topography. "Tuscaloosa, AL: Seasonal Inundation Dynamics And Invertebrate Communities," 2011. https://doi.org/10.5069/G9SF2T3K.

See Also

Functions

geotiffwrite|mapshow|pc2dem|segmentGroundSMRF

Objects

MapPostingsReference|projcrs|lasFileReader

Converting Coastline Data (GSHHG) to Shapefile Format

This example shows how to:

- Extract a subset of coastline data from the Global Self-consistent Hierarchical High-resolution Geography (GSHHG) data set
- Manipulate polygon features to add lakes and other interior water bodies as inner polygon rings ("holes")
- Save the modified data set to a shapefile for future use in MATLAB®, or for export to a geographic information system

The Global Self-consistent Hierarchical High-resolution Geography (GSHHG; formerly Global Self-consistent Hierarchical High-resolution Shorelines, or GSHHS) data set, by Paul Wessel and Walter H. F. Smith, provides a consistent set of hierarchically arranged closed polygons. They can be used to construct base maps, or in applications or analyses that involve operations like geographic searches or the statistical properties of coastlines.

Step 1: Define a Working Folder

This example creates several temporary files and uses the variable workingFolder to denote their location. The value used here is determined by the output of the tempdir command, but you could easily customize this.

```
workingFolder = tempdir;
```

Step 2: GNU® Unzip and Index the Coarse-Resolution GSHHG Layer

GSHHG is available in wide range of spatial resolutions. This example uses the lowest-resolution data, from the binary file $gshhs_c.b.$ A GNU zipped copy of this file is included in the Mapping Toolbox data folder, on the MATLAB path.

Use the MATLAB gunzip function to decompress gshhs_c.b.gz and create the file gshhs_c.b in the location indicated by workingFolder. Then create an index file, gshhs_c.i, in the same folder. In general, having an index file helps to accelerate later calls to the gshhs function. Note that when you use the 'createindex' option, gshhs does not extract data.

```
files = gunzip('gshhs_c.b.gz', workingFolder);
filename = files{1};
indexfile = gshhs(filename, 'createindex');
```

Step 3: Import the GSHHG Data for South America

Select data for a specific latitude-longitude quadrangle and import it as a Mapping Toolbox "geostruct" array:

```
latlim = [-60 15];
lonlim = [-90 -30];
S = gshhs(filename, latlim, lonlim);
```

If you have finished extracting data, you can remove the decompressed GSHHS file and the index file.

```
delete(filename)
delete(indexfile)
```

Step 4: Examine the Data Set

Examine the first element of the geostruct array S. In addition to the Lat and Lon coordinate arrays, note the various attribute fields that are present.

S(1)

```
ans = struct with fields:
            Geometry: 'Polygon'
         BoundingBox: [2x2 double]
                 Lat: [-53.0004 -53 -52.5017 -52.7963 -52.0434 -52.0838 ...]
                 Lon: [-73.3617 -73.3626 -72.8909 -73.7034 -73.7392 ...]
               South: -53.9004
               North: 71.9942
                West: 191.8947
                East: 325.2054
                Area: 3.7652e+07
               Level: 1
         LevelString: 'land'
           NumPoints: 971
       FormatVersion: 3
              Source: 'WVS'
    CrossesGreenwich: 0
            GSHHS ID: 1
```

GSHHS comprises four levels of shorelines:

- Level 1 "Land"
- Level 2 "Lake"
- Level 3 "Island in lake"
- Level 4 "Pond in island in lake"

Check to see which levels the data you've imported includes. The Level field contains numerical level numbers.

```
levels = [S.Level];
unique(levels)
ans = 1×3
1 2 3
```

The LevelString field provides their interpretation. For example,

```
S(104).LevelString
```

```
ans = 'lake'
```

shows that feature 104 is a lake (a Level 2 feature).

In this example, due either to the low resolution or to spatial subsetting, no Level 4 features are present.

Step 5: Extract the Top Two Levels into Separate Geostruct Arrays

This example manipulates the top two levels of the GSHHS hierarchy, inserting each "lake" into the surrounding land mass.

Extract GSHHS Level 1 (exterior coastlines of continents and oceanic islands):


```
L1 = S(levels == 1);
```

Extract Level 2 (coastlines of lakes and seas within Level 1 polygons):

```
L2 = S(levels == 2);
```

To see their spatial relationships, you can map Level 1 edges as blue lines and Level 2 edges as red lines:

```
figure
axesm('mercator', 'MapLatLimit', latlim, 'MapLonLimit', lonlim)
gridm; mlabel; plabel
geoshow([L1.Lat], [L1.Lon], 'Color', 'blue')
geoshow([L2.Lat], [L2.Lon], 'Color', 'red')
tightmap
```



Step 6: Merge Level 2 Polygons into Level 1

Define an anonymous predicate function to detect bounding-box intersections (returning true if a pair of bounding boxes intersect and false otherwise). Inputs A and B are 2-by-2 bounding-box matrices of the form

```
[min(lon) min(lat)
  max(lon) max(lat)].

boxesIntersect = ...
  @(A,B) (~(any(A(2,:) < B(1,:)) || any(B(2,:) < A(1,:))));</pre>
```

For convenience in looping over them, copy the Level 1 bounding boxes to a 3-D array:

```
L1boxes = reshape([L1.BoundingBox],[2 2 numel(L1)]);
```

Check each Level 1 - Level 2 pair of features for possible intersection. See if polybool returns any output or not, but avoid calling polybool unless a bounding box intersection is detected first:

Step 7: Save Results in a Shapefile

With a single call to shapewrite, you can create a trio of files,

```
gshhs_c_SouthAmerica.shp
gshhs_c_SouthAmerica.shx
gshhs_c_SouthAmerica.dbf

in your working folder.
shapepath = fullfile(workingFolder, 'gshhs_c_SouthAmerica.shp');
shapewrite(L1, shapepath)
```

Step 8: Validate the Shapefile

To validate the results of shapewrite, read the new shapefile into the geospatial table southAmerica:

southAmerica = readgeotable(shapepath, 'CoordinateSystemType', 'geographic')

southAmerica=79×13 table							
Shape	South	North	West	East	Area	Level	LevelString
geopolyshape	-53.9	71.994	191.89	325.21	3.7652e+07	1	"land"
geopolyshape	-55.055	-52.469	287.98	294.89	46269	1	"land"
geopolyshape	-52.36	-51.235	300.26	302.29	4402.4	1	"land"
geopolyshape	-55.675	-54.933	289.99	292.02	2669.1	1	"land"
geopolyshape	-50.065	-48.67	284.53	285.62	4021.9	1	"land"
geopolyshape	-52.26	-51.336	298.92	300.81	4326.2	1	"land"

```
-54.135
                            -53.38
                                      286.33
                                                 287.85
                                                               3809.7
                                                                                     "land"
geopolyshape
geopolyshape
                -43.448
                           -41.768
                                      285.55
                                                 286.65
                                                                10188
                                                                           1
                                                                                     "land"
geopolyshape
                -53.478
                            -52.73
                                         287
                                                 288.46
                                                               3006.8
                                                                           1
                                                                                     "land"
geopolyshape
                 10.041
                            10.841
                                      298.07
                                                 299.09
                                                                 5174
                                                                           1
                                                                                     "land"
                -54.276
                           -53.566
                                                               1420.3
                                                                           1
                                                                                     "land"
geopolyshape
                                       289.1
                                                 289.8
                                      286.54
                                                                955.5
                                                                           1
                                                                                     "land"
geopolyshape
                -44.937
                           -44.364
                                                 287.31
                                                                                     "land"
                           -53.936
                                      288.29
                                                                704.5
                                                                           1
geopolyshape
                -54.401
                                                 289.04
                                                                           1
                                                                                     "land"
                -51.125
                            -50.71
                                      285.04
                                                 285.64
                                                                  462
geopolyshape
                                       284.54
                                                                612.9
                                                                           1
                                                                                     "land"
geopolyshape
                -50.458
                           -50.001
                                                 285.24
                                                                           1
geopolyshape
                -48.711
                           -48.137
                                      284.98
                                                 285.53
                                                               1039.8
                                                                                     "land"
```


Note that the two longest fieldnames, 'FormatVersion' and 'CrossesGreenwich', have been truncated to 11 characters. This happened during the call to shapewrite and is unavoidable because of a rigid 11-character limit in the xBASE tables (.DBF format) used to store attributes in shapefiles. (In general, when writing shapefiles you may want to re-define fieldnames longer than 11 characters in order to avoid or control the effects of automatic truncation.)

Optionally, remove the new shapefiles from your working folder. (This example needs to clean up after itself; in a real application you would probably want to omit this step.)

```
delete([shapepath '.*'])
```

Display the data from the new shapefile. Note the various "holes" in the South America polygon indicating lakes and shorelines of other extended bodies of water in the interior of the continent.

```
figure
ax = axesm('mercator', 'MapLatLimit', latlim, 'MapLonLimit', lonlim);
ax.Color = 'cyan';
gridm; mlabel; plabel
geoshow(southAmerica, 'FaceColor', [0.15 0.8 0.15])
tightmap
```



Reference

Wessel, P., and W. H. F. Smith, 1996, A global self-consistent, hierarchical, high-resolution shoreline database, Journal of Geophysical Research, Vol. 101, pp. 8741-8743.

Additional Data

The complete GSHHG data set may be downloaded from the U.S. National Oceanic and Atmospheric Administration (NOAA) web site. For more information about finding data sets, see "Find Geospatial Vector Data" on page 2-78.

Credits

The GSHHG data file is provided in the Mapping Toolbox courtesy of Dr. Paul Wessel of the University of Hawaii and Dr. Walter H. F. Smith of NOAA.

For more information, run:

>> type gshhs_c.txt

See Also

gshhs|shapewrite|readgeotable

Understanding Geospatial Geometry


- "The Shape of the Earth" on page 3-2
- "Reference Spheroids" on page 3-4
- "Work with Reference Spheroids" on page 3-11
- "Latitude and Longitude" on page 3-13
- "Relationship Between Points on Sphere" on page 3-15
- "Length and Distance Units" on page 3-16
- "Angle Representations and Angular Units" on page 3-18
- "Distances on the Sphere" on page 3-21
- "Great Circles" on page 3-24
- "Rhumb Lines" on page 3-25
- "Azimuth" on page 3-26
- "Elevation" on page 3-28
- "Generate Vector Data for Points Along Great Circle or Rhumb Line Tracks" on page 3-29
- "Reckoning" on page 3-31
- "Calculate Distance Between Two Points in Geographic Space" on page 3-32
- "Generate Small Circles" on page 3-33
- "Measure Area of Spherical Quadrangles" on page 3-35
- "Plotting a 3-D Dome as a Mesh over a Globe" on page 3-36
- "Comparison of 3-D Coordinate Systems" on page 3-42
- "Vectors in 3-D Coordinate Systems" on page 3-47
- "Find Ellipsoidal Height from Orthometric Height" on page 3-50

The Shape of the Earth

Although the Earth is very round, it is an oblate spheroid rather than a perfect sphere. This difference is so small (only one part in 300) that modeling the Earth as spherical is sufficient for making small-scale (world or continental) maps. However, making accurate maps at larger scale demands that a spheroidal model be used. Such models are essential, for example, when you are mapping high-resolution satellite or aerial imagery, or when you are working with coordinates from the Global Positioning System (GPS). This section addresses how Mapping Toolbox software accurately models the shape, or figure, of the Earth.

Ellipsoid Shape

You can define ellipsoids in several ways. They are usually specified by a semimajor and a semiminor axis, but are often expressed in terms of a semimajor axis and either inverse flattening (which for the Earth, as mentioned above, is one part in 300) or eccentricity. Whichever parameters are used, as long as an axis length is included, the ellipsoid is fully constrained and the other parameters are derivable. The components of an ellipsoid are shown in the following diagram.



The toolbox includes ellipsoid models that represent the figures of the Sun, Moon, and planets, as well as a set of the most common ellipsoid models of the Earth. For more information, see "Reference Spheroids" on page 3-4.

Geoid Shape

Literally, *geoid* means *Earth-shaped*. The geoid is an empirical approximation of the figure of the Earth (minus topographic relief), its "lumpiness." Specifically, it is an equipotential surface with respect to gravity, more or less corresponding to mean sea level. It is approximately an ellipsoid, but not exactly so because local variations in gravity create minor hills and dales (which range from -100 m to +60 m across the Earth). This variation in height is on the order of 1 percent of the differences between the semimajor and semiminor ellipsoid axes used to approximate the Earth's shape.

The shape of the geoid is important for some purposes, such as calculating satellite orbits, but need not be taken into account for every mapping application. However, knowledge of the geoid is

sometimes necessary, for example, when you compare elevations given as height above mean sea level to elevations derived from GPS measurements. Geoid representations are also inherent in datum definitions.

Map the Geoid

Get geoid heights and a geographic postings reference object from the EGM96 geoid model. Load coastline latitude and longitude data.


```
[N,R] = egm96geoid;
load coastlines
```

Display the geoid heights as a surface using a Robinson projection. Ensure the coastline data appears over the surface by setting the 'CData' name-value pair to the geoid heights data and the 'ZData' name-value pair to a matrix of zeros. Then, display the coastline data.

```
axesm robinson
Z = zeros(R.RasterSize);
geoshow(N,R,'DisplayType','surface','CData',N,'ZData',Z)
geoshow(coastlat,coastlon,'color','k')
```

Display a colorbar below the map.

```
colorbar('southoutside')
```



Reference Spheroids

When the Earth (or another roughly spherical body such as the Moon) is modeled as a sphere having a standard radius, it is called a *reference sphere*. Likewise, when the model is a flattened (oblate) ellipsoid of revolution, with a standard semimajor axis and standard inverse flattening, semiminor axis, or eccentricity, it is called a *reference ellipsoid*. Both models are spheroidal in shape, so each can be considered to be a type of *reference spheroid*. Mapping Toolbox supports several representations for reference spheroids: referenceSphere, referenceEllipsoid, and oblateSpheroid objects, and an older representation, *ellipsoid vector*.

```
In this section...

"referenceSphere Objects" on page 3-4

"referenceEllipsoid Objects" on page 3-6

"World Geodetic System 1984" on page 3-8

"Ellipsoid Vectors" on page 3-9

"oblateSpheroid Objects" on page 3-10
```

referenceSphere Objects

When using a strictly spherical model, you should generally use a referenceSphere object (although both referenceEllipsoid and oblateSpheroid can represent a perfect sphere).

By default, referenceSphere returns a dimensionless unit sphere:

```
referenceSphere
```

```
ans =
referenceSphere with defining properties:
    Name: 'Unit Sphere'
LengthUnit: ''
    Radius: 1

and additional properties:

SemimajorAxis
SemiminorAxis
InverseFlattening
Eccentricity
Flattening
ThirdFlattening
MeanRadius
SurfaceArea
Volume
```

You can request a specific body by name, and the radius will be in meters by default:

```
earth = referenceSphere('Earth')
earth =
referenceSphere with defining properties:
```

```
Name: 'Earth'
    LengthUnit: 'meter'
        Radius: 6371000
  and additional properties:
    SemimajorAxis
    SemiminorAxis
    InverseFlattening
    Eccentricity
    Flattening
    ThirdFlattening
    MeanRadius
    SurfaceArea
    Volume
You can reset the length unit if desired (and the radius is rescaled appropriately):
earth.LengthUnit = 'kilometer'
earth =
referenceSphere with defining properties:
          Name: 'Earth'
    LengthUnit: 'kilometer'
        Radius: 6371
  and additional properties:
    SemimajorAxis
    SemiminorAxis
    InverseFlattening
    Eccentricity
    Flattening
    ThirdFlattening
    MeanRadius
    SurfaceArea
    Volume
or specify the length unit at the time of construction:
referenceSphere('Earth','km')
ans =
referenceSphere with defining properties:
          Name: 'Earth'
    LengthUnit: 'kilometer'
        Radius: 6371
  and additional properties:
    SemimajorAxis
    SemiminorAxis
    InverseFlattening
    Eccentricity
```

```
Flattening
ThirdFlattening
MeanRadius
SurfaceArea
Volume
```

Any length unit supported by validateLengthUnit can be used. A variety of abbreviations are supported for most length units, see validateLengthUnit for a complete list.

One thing to note about referenceSphere is that only the defining properties are displayed, in order to reduce clutter at the command line. (This approach saves a small amount of computation as well.) In particular, don't overlook the dependent SurfaceArea and Volume properties, even though they are not displayed. The surface area of the spherical earth model, for example, is easily obtained through the SurfaceArea property:

earth.SurfaceArea

```
ans = 5.1006e+08
```

This result is in square kilometers, because the LengthUnit property of the object earth has value 'kilometer'.

When programming with Mapping Toolbox it may help to be aware that referenceSphere actually includes all the geometric properties of referenceEllipsoidand oblateSpheroid (SemimajorAxis, SemiminorAxis, InverseFlattening, Eccentricity, Flattening, ThirdFlattening, and MeanRadius, as well as SurfaceArea, and Volume). None of these properties can be set on a referenceSphere, and some have values that are fixed for all spheres. Eccentricity is always 0, for example. But they provide a flexible environment for programming because any geometric computation that accepts a referenceEllipsoid will also run properly given a referenceSphere. This is a type of polymorphism in which different classes support common, or strongly overlapping interfaces.

referenceEllipsoid Objects

When using an oblate spheroid to represent the Earth (or another roughly spherical body), you should generally use a referenceEllipsoid object. An important exception occurs with certain small-scale map projections, many of which are defined only on the sphere. However, all important projections used for large-scale work, including Transverse Mercator and Lambert Conformal Conic, are defined on the ellipsoid as well as the sphere.

Like referenceSphere, referenceEllipsoid returns a dimensionless unit sphere by default:

referenceEllipsoid

```
and additional properties:

Flattening
ThirdFlattening
MeanRadius
SurfaceArea
Volume
```

More typically, you would request a specific ellipsoid by name, resulting in an object with semimajor and semiminor axes properties in meters. For example, the following returns a referenceEllipsoid with SemimajorAxis and InverseFlattening property settings that match the defining parameters of Geodetic Reference System 1980 (GRS 80).

```
grs80 = referenceEllipsoid('Geodetic Reference System 1980')
grs80 =
referenceEllipsoid with defining properties:
                 Code: 7019
                 Name: 'Geodetic Reference System 1980'
           LengthUnit: 'meter'
        SemimajorAxis: 6378137
        SemiminorAxis: 6356752.31414036
    InverseFlattening: 298.257222101
         Eccentricity: 0.0818191910428158
 and additional properties:
   Flattening
   ThirdFlattening
   MeanRadius
   SurfaceArea
   Volume
```

In general, you should use the reference ellipsoid corresponding to the geodetic datum to which the coordinates of your data are referenced. For instance, the GRS 80 ellipsoid is specified for use with coordinates referenced to the North American Datum of 1983 (NAD 83).

As in the case of referenceSphere, you can reset the length unit if desired:

```
Flattening
    ThirdFlattening
    MeanRadius
    SurfaceArea
    Volume
or specify the length unit at the time of construction:
referenceEllipsoid('Geodetic Reference System 1980', 'km')
ans =
referenceEllipsoid with defining properties:
                 Code: 7019
                 Name: 'Geodetic Reference System 1980'
           LengthUnit: 'kilometer'
        SemimajorAxis: 6378.137
        SemiminorAxis: 6356.75231414036
    InverseFlattening: 298.257222101
         Eccentricity: 0.0818191910428158
  and additional properties:
    Flattening
    ThirdFlattening
    MeanRadius
    SurfaceArea
    Volume
```

Any length unit supported by validateLengthUnit can be used.

The command-line display includes four geometric properties: SemimajorAxis, SemiminorAxis, InverseFlattening, and Eccentricity. Any pair of these properties, as long as at least one is an axis length, is sufficient to fully define a oblate spheroid; the four properties constitute a mutually dependent set. Parameters InverseFlattening and Eccentricity as a set are not sufficient to define an ellipsoid because both are dimensionless shape properties. Neither of those parameters provides a length scale, and, furthermore, are mutually dependent: ecc = sqrt((2 - f) * f).

In addition, there are five dependent properties that are not displayed, in order to reduce clutter on the command line: Flattening, ThirdFlattening, MeanRadius, SurfaceArea, and Volume. SurfaceArea and Volume work the same way as their referenceSphere counterparts. To continue the preceding example, the surface area of the GRS 80 ellipsoid in square kilometers (because LengthUnit is 'kilometer'), is easily obtained as follows:

```
grs80.SurfaceArea
ans =
   5.1007e+08
```

See the referenceEllipsoid reference page for definitions of the shape properties, permissible values for the Name property, and information on the Code property.

World Geodetic System 1984

Due in part to widespread use of the U.S. NAVSTAR Global Positioning System (GPS), which is tied to World Geodetic System 1984 (WGS 84), the WGS 84 reference ellipsoid is often the appropriate

choice. For both convenience and speed (obtained by bypassing a table look-up step), it's a good idea in this case to use the wgs84Ellipsoid function, for example,

```
wgs84 = wgs84Ellipsoid;
The preceding line is equivalent to:
wgs84 = referenceEllipsoid('wgs84');
```

but it is easier to type and faster to run. You can also specify a length unit.
wgs84Ellipsoid(lengthUnit), is equivalent to referenceEllipsoid('wgs84',lengthUnit),
where lengthUnit is any unit value accepted by the validateLengthUnit function.

For example, the follow two commands show that the surface area of the WGS 84 ellipsoid is a little over 5×10^14 square meters:

```
s = wgs84Ellipsoid
s =
referenceEllipsoid with defining properties:
                 Code: 7030
                 Name: 'World Geodetic System 1984'
           LengthUnit: 'meter'
        SemimajorAxis: 6378137
        SemiminorAxis: 6356752.31424518
    InverseFlattening: 298.257223563
         Eccentricity: 0.0818191908426215
 and additional properties:
    Flattening
    ThirdFlattening
   MeanRadius
    SurfaceArea
   Volume
s.SurfaceArea
ans =
   5.1007e+14
```

Ellipsoid Vectors

An ellipsoid vector is simply a 2-by-1 double of the form: [semimajor_axis eccentricity]. Unlike a spheroid object (any instance of referenceSphere, referenceEllipsoid, or oblateSpheroid), an ellipsoid vector is not self-documenting. Ellipsoid vectors are not even self-identifying. You have to know that a given 2-by-1 vector is indeed an ellipsoid vector to make any use of it. This representation does not validate that semimajor_axis is real and positive, for example, you have to do such validations for yourself.

Many toolbox functions accept ellipsoid vectors as input, but such functions accept spheroid objects as well and, for the reasons just stated, spheroid objects are recommended over ellipsoid vectors. In case you have written a function of your own that requires an ellipsoid vector as input, or have

received such a function from someone else, note that you can easily convert any spheroid object s into an ellipsoid vector as follows:

```
[s.SemimajorAxis s.Eccentricity]
```

This means that you can construct a spheroid object using any of the three class constructors, or the wgs84Ellipsoid function, and hand off the result in the form of an ellipsoid vector if necessary.

oblateSpheroid Objects

oblateSpheroid is the superclass of referenceEllipsoid. An oblateSpheroid object is just like a referenceEllipsoid object minus its Code, Name, and LengthUnit properties. In fact, the primary role of the oblateSpheroid class is to provide the purely geometric properties and behaviors needed by the referenceEllipsoid class.

For most purposes, you can simply ignore this distinction, and the oblateSpheroid class itself, as a matter of internal software composition. No harm will come about, because a referenceEllipsoid object can do anything and be used anywhere that an oblateSpheroid can.

However, you can use oblateSpheroid directly when dealing with an ellipsoid vector that lacks a specified name or length unit. For example, compute the volume of a ellipsoid with a semimajor axis of 2000 and eccentricity of 0.1, as shown in the following.

```
e = [2000 \ 0.1];
s = oblateSpheroid;
s.SemimajorAxis = e(1);
s.Eccentricity = e(2)
s.Volume
s =
oblateSpheroid with defining properties:
        SemimajorAxis: 2000
        SemiminorAxis: 1989.97487421324
    InverseFlattening: 199.498743710662
         Eccentricity: 0.1
  and additional properties:
    Flattening
    ThirdFlattening
    MeanRadius
    SurfaceArea
    Volume
ans =
   3.3342e+10
```

Of course, since the length unit of e is unspecified, the unit of s. Volume is likewise unspecified.

Work with Reference Spheroids

Reference spheroids are needed in three main contexts: map projections, curves and areas on the surface of a spheroid, and 3-D computations involving geodetic coordinates.

Map Projections

You can set the value of the Geoid property of a new axesm-based map (which is actually a Spheroid property) using any type of reference spheroid representation. Except in the case of UTM and UPS, the default value is an ellipsoid vector representing the unit sphere: [1 0]. It is also the default value when using the worldmap and usamap functions.

You can reset the Geoid property of an existing axesm-based map to any type of reference spheroid representation by using setm. For example, worldmap always sets up a projection based on the unit sphere but you can subsequently use setm to switch to the spheroid of your choice. To set up a map of North America for use with Geodetic Reference System 1980, for instance, follow worldmap with a call to setm, like this:

```
ax = worldmap('North America');
setm(ax,'geoid',referenceEllipsoid('grs80'))
```

When projecting or unprojecting data without an axesm-based map, you can set the geoid field of a map projection structure (mstruct) to any type of reference spheroid representation. Remember to follow all mstruct updates with a second call to defaultm to ensure that all properties are set to legitimate values. For example, to use the Miller projection with WGS 84 in kilometers, start with:

```
mstruct = defaultm('miller');
mstruct.geoid = wgs84Ellipsoid('km');
mstruct = defaultm(mstruct);
```

Volume

You can inspect the mstruct to ensure that you are indeed using the WGS 84 ellipsoid:

See axesm-Based Map Properties for definitions of the fields found in mstructs.

Curves and Areas

Another important context in which reference spheroids appear is the computation of curves and areas on the surface of a sphere or oblate spheroid. The distance function, for example, assumes a sphere by default, but accepts a reference spheroid as an optional input. distance is used to compute the length of the geodesic or rhumb line arc between a pair of points with given latitudes and longitudes. If a reference spheroid is provided through the ellipsoid argument, then the unit used for the arc length output matches the LengthUnit property of the spheroid.

Other functions for working with curves and areas that accept reference spheroids include reckon, scircle1, scircle2, ellipse1, track1, track2, and areaquad, to name just a few. When using such functions without their ellipsoid argument, be sure to check the individual function help if you are unsure about which reference spheroid is assumed by default.

3-D Coordinate Transformations

The third context in which reference spheroids frequently appear is the transformation of geodetic coordinates (latitude, longitude, and height above the ellipsoid) to other coordinate systems. For example, the <code>geodetic2ecef</code> function, which converts point locations from a geodetic system to a geocentric (Earth-Centered Earth-Fixed) Cartesian system, requires a reference spheroid object (or an ellipsoid vector) as input.

Latitude and Longitude

Two angles, latitude and longitude, specify the position of a point on the surface of a planet. These angles can be in degrees or radians; however, degrees are far more common in geographic notation.

Latitude is the angle between the plane of the equator and a line connecting the point in question to the planet's rotational axis. There are different ways to construct such lines, corresponding to different types of and resulting values for latitudes. Latitude is positive in the northern hemisphere, reaching a limit of $+90^{\circ}$ at the north pole, and negative in the southern hemisphere, reaching a limit of -90° at the south pole. Lines of constant latitude are called parallels.


Longitude is the angle at the center of the planet between two planes that align with and intersect along the axis of rotation, perpendicular to the plane of the equator. One plane passes through the surface point in question, and the other plane is the *prime meridian* (0° longitude), which is defined by the location of the Royal Observatory in Greenwich, England. Lines of constant longitude are called *meridians*. All meridians converge at the north and south poles (90°N and -90°S), and consequently longitude is under-specified in those two places.

Longitudes typically range from -180° to +180°, but other ranges can be used, such as 0° to +360°. Longitudes can also be specified as east of Greenwich (positive) and west of Greenwich (negative). Adding or subtracting 360° from its longitude does not alter the position of a point. The toolbox includes a set of functions (wrapTo180, wrapTo360, wrapToPi, and wrapTo2Pi) that convert longitudes from one range to another. It also provides unwrapMultipart, which "unwraps" vectors of longitudes in radians by removing the artificial discontinuities that result from forcing all values to lie within some 360°-wide interval.

Plot Latitude and Longitude

This example shows how to plot latitude and longitude.

```
load coastlines
axesm('ortho','origin',[45 45]);
axis off;
gridm on;
framem on;
mlabel('equator')
plabel(0);
plabel('fontweight','bold')
plotm(coastlat,coastlon)
```



Relationship Between Points on Sphere

When using spherical coordinates, distances are expressed as angles, not lengths. As there is an infinity of arcs that can connect two points on a sphere or spheroid, by convention the shortest one (the great circle distance) is used to measure how close two points are. As is explained in "Distances on the Sphere" on page 3-21, you can convert angular distance on a sphere to linear distance. This is different from working on an ellipsoid, where one can only speak of linear distances between points, and to compute them one must specify which reference ellipsoid to use.

In spherical or geodetic coordinates, a position is a latitude taken together with a longitude, e.g., (lat,lon), which defines the horizontal coordinates of a point on the surface of a planet. When we consider two points, e.g., (lat1,lon1) and (lat2,lon2), there are several ways in which their 2-D spatial relationships are typically quantified:

- The azimuth (also called heading) to take to get from (lat1,lon1) to (lat2,lon2)
- The back azimuth (also called heading) from (lat2,lon2) to (lat1,lon1)
- The spherical distance separating (lat1,lon1) from (lat2,lon2)
- The linear distance (range) separating (lat1,lon1) from (lat2,lon2)

The first three are angular quantities, while the last is a length. Mapping Toolbox functions exist for computing these quantities. For additional examples, see "Navigation" on page 10-9.

There is no single default unit of distance measurement in the toolbox. Navigation functions use nautical miles as a default and the distance function uses degrees of arc length. For many functions, the default unit for distances and positions is degrees, but you need to verify the default assumptions before using any of these functions.

Note When distances are given in terms of angular units (degrees or radians), be careful to remember that these are specified in terms of arc length. While a degree of latitude always subtends one degree of arc length, this is only true for degrees of longitude along the equator.

Length and Distance Units

Linear measurements of lengths and distances on spheres and spheroids can use the same units they do on the plane, such as feet, meters, miles, and kilometers. They can be used for

- Absolute positions, such as map coordinates or terrain elevations
- Dimensions, such as a planet's radius or its semimajor and semiminor axes
- Distances between points or along routes, in 2-D or 3-D space or across terrain

Length units are needed to describe

- · The dimensions of a reference sphere or ellipsoid
- The line-of-sight distance between points
- Distances along great circle or rhumb line curves on an ellipsoid or sphere
- X-Y locations in a projected coordinate system or map grid
- Offsets from a map origin (false eastings and northings)
- X-Y-Z locations in Earth-centered Earth-fixed (ECEF) or local vertical systems
- Heights of various types (terrain elevations above a geoid, an ellipsoid, or other reference surface)

Choosing Units of Length

Using the toolbox effectively depends on being consistent about units of length. Depending on the specific function and the way you are calling it, when you specify lengths, you could be

- · Explicitly specifying a radius, reference spheroid object, or ellipsoid vector
- · Relying on the function itself to specify a default radius or ellipsoid
- Relying on the reference ellipsoid associated with a map projection structure (mstruct)

Whenever you are doing a computation that involves a reference sphere or ellipsoid, make sure that the units of length you are using are the same units used to define the radius of the sphere or semimajor axis of the ellipsoid. These considerations are discussed below.

Converting Units of Length

The following Mapping Toolbox functions convert between different units of length:

• unitsratio computes multiplicative factors for converting between 12 different units of length as well as between degrees and radians. You can use unitsratio to perform conversions when neither the input units of length nor the output units of length are known until run time. For example,

```
fromUnits = 'radians';
toUnits = 'degrees';
piInDegrees = unitsratio(toUnits, fromUnits) * pi
piInDegrees =
   180
```

• km2nm, km2sm, nm2km, nm2sm, sm2km, and sm2nm perform simple and convenient conversions between kilometers, nautical miles, and statute miles.

These utility functions accept scalars, vectors, and matrices, or any shape. For an overview of these functions and angle conversion functions, see "Summary: Available Distance and Angle Conversion Functions" on page 3-22.

Angle Representations and Angular Units

In this section...

"Degrees and Radians" on page 3-18

"Degree Representations" on page 3-18

"Latitude and Longitude Formats" on page 3-19

This topic describes the angular units that Mapping Toolbox functions use, how to convert between common angle representations, and how to format latitude and longitude angles as text.

Use angles in mapping applications to indicate absolute positions, relative positions along reference ellipsoids, and relative positions in 3-D:

- Absolute positions are latitudes and longitudes.
- Relative positions on reference ellipsoids are azimuths along geodesics, great circles, and rhumb lines. Find these relative positions by using the distance function.
- Relative positions in 3-D are both azimuths and elevations. Find these relative positions by using the geodetic2aer function.

Degrees and Radians

The most common angular units are degrees and radians. Many Mapping Toolbox functions perform angle computations in degrees. If your data is in radians, you can convert to degrees by using the rad2deg function.

Many Mapping Toolbox functions, such as distance and azimuth, use degrees by default and allow you to choose radians. Some functions, such as unwrapMultipart and meridianarc, use radians by default or require you to work in radians.

Degree Representations

Angles are commonly represented using degrees (-35.2625°), degrees-minutes (-35° 15.75'), and degrees-minutes-seconds (-35° 15' 45"). Minutes are 1/60 of a degree and seconds are 1/60 of a minute.

Because Mapping Toolbox functions perform angle computations using only degrees, if your data has values in degrees-minutes (DM) or degrees-minutes-seconds (DMS), you must convert the values to degrees before using them as input. Convert numeric values from DM or DMS to degrees by using the dm2degrees or dms2degrees function. You can also convert text values from DM or DMS to degrees by using the str2angle function.

If you want to publish coordinate values or format data for use with other applications, then you can convert degrees to DM or DMS. Convert degrees to DM or DMS by using the degrees2dm or degrees2dms function.

Degrees

Degrees represent angles using a sign or direction and a nonnegative decimal number. For example, you can represent a longitude of 35.2625 degrees west of the prime meridian as -35.2625° or 35.2625° W.

Note Decimal degrees is a common way to refer to noninteger latitude and longitude values. The term is appropriate for angles formatted in text using decimal notation, such as when printed in a document or displayed at the MATLAB command line. However, the term is inaccurate for angles in degrees that are stored in computer memory, such as in MATLAB variables. Angles are stored in memory as single or double precision floating-point numbers, which are binary representations, not decimal representations. Therefore, the term *degrees* is more accurate than decimal degrees for angles stored in memory, even when the angles have noninteger values.

Degrees-Minutes

Degrees-minutes represent angles using a sign or direction and two numbers:

- Degrees (°) A signed or unsigned integer
- Minutes (') A nonnegative decimal number in the range [0 60)

For example, a longitude of -35.2625 in degrees is -35° 15.75' or 35° 15.75' W in DM. This code shows how to convert numbers in DM to degrees by using the dm2degrees function.

```
dm2degrees([-35 15.75])
ans =
    -35.2625
```

Degrees-Minutes-Seconds

Degrees-minutes-seconds represent angles using a sign or direction and three numbers:

- Degrees (°) A signed or unsigned integer
- Minutes (') A nonnegative integer in the range [0 59]
- Seconds (") A nonnegative decimal number in the range [0 60)

For example, a longitude of -35.2625 in degrees is -35° 15' 45" or 35° 15' 45" W in DMS. This code shows how to convert numbers in DMS to degrees by using the dms2degrees function.

```
dms2degrees([-35 15 45])
ans =
   -35,2625
```

Latitude and Longitude Formats

You can format latitudes and longitudes by using letters or symbols:

```
Degrees — d or °
Minutes — m or '
```

• Seconds — s or "

You can also indicate the sign of the angle by using letters:

• Positive latitude — N

- Negative latitude S
- Positive longitude E
- Negative longitude W

For example, you can format 35 degrees, 15 minutes, 45 seconds west of the prime meridian as 35d15m45sW, $35^{\circ}15'45''W$, or $-35^{\circ}15'45''$.

Convert latitudes and longitudes in degrees to character arrays in DM or DMS for use with LaTeX by using the angl2str function. This code shows how to convert a longitude of -36.2625 degrees to a character array that uses DMS.

```
angl2str(-35.2625,"ew","degrees2dms")
ans =
   ' 35^{\circ} 15' 45.00" W '
```

If you want to format angles in ways that the angl2str function does not support, first convert the angle from decimal degrees to numbers in DM or DMS by using the degrees2dms or degrees2dm function. Then, format the numbers into a string or character vector by using the sprintf function.

This code shows how to convert the same longitude to a character array that uses Unicode® instead of LaTeX.

```
dm = degrees2dms(-35.2625);
sprintf('%d\x00B0 %u\x0027 %.2f\x0022 W',dm)
ans =
   '-35° 15' 45.00" W'
```

See Also

Functions

toDegrees

Distances on the Sphere

In this section... "Arc Length as an Angle in the distance and reckon Functions" on page 3-22 "Summary: Available Distance and Angle Conversion Functions" on page 3-22

Many geospatial domains (seismology, for example) describe distances between points on the surface of the earth as angles. This is simply the result of dividing the length of the shortest great-circle arc connecting a pair points by the radius of the Earth (or whatever planet one is measuring). This gives the angle (in radians) subtended by rays from each point that join at the center of the Earth (or other planet). This is sometimes called a "spherical distance." You can thus call the resulting number a "distance in radians." You could also call the same number a "distance in earth radii." When you work with transformations of geodata, keep this in mind.

You can easily convert that angle from radians to degrees. For example, you can call distance to compute the distance in meters from London to Kuala Lumpur:

```
latL = 51.5188;
lonL = -0.1300;
latK =
       2.9519;
lonK = 101.8200;
earthRadiusInMeters = 6371000;
distInMeters = distance(latL, lonL,...
                latK, lonK, earthRadiusInMeters)
distInMeters =
  1.0571e+007
Then convert the result to an angle in radians:
distInRadians = distInMeters / earthRadiusInMeters
distInRadians =
    1.6593
Finally, convert to an angle in degrees:
distInDegrees = rad2deg(distInRadians)
distInDearees =
   95.0692
```

This really only makes sense and produces accurate results when we approximate the Earth (or planet) as a sphere. On an ellipsoid, one can only describe the distance along a geodesic curve using a unit of length.

Mapping Toolbox software includes a set of six functions to conveniently convert distances along the surface of the Earth (or another planet) from units of kilometers (km), nautical miles (nm), or statute miles (sm) to spherical distances in degrees (deg) or radians (rad):

- km2deg, nm2deg, and sm2deg go from length to angle in degrees
- km2rad, nm2rad, and sm2rad go from length to angle in radians

You could replace the final two steps in the preceding example with

```
distInKilometers = distInMeters/1000;
earthRadiusInKm = 6371;
km2deg(distInKilometers, earthRadiusInKm)
ans =
    95.0692
```

Because these conversion can be reversed, the toolbox includes another six convenience functions that convert an angle subtended at the center of a sphere, in degrees or radians, to a great-circle distance along the surface of that sphere:

- deg2km, deg2nm, and deg2sm go from angle in degrees to length
- rad2km, rad2nm, and rad2sm go from angle in radians to length

When given a single input argument, all 12 functions assume a radius of 6,371,000 meters (6371 km, 3440.065 nm, or 3958.748 sm), which is widely-used as an estimate of the average radius of the Earth. An optional second parameter can be used to specify a planetary radius (in output length units) or the name of an object in the Solar System.

Arc Length as an Angle in the distance and reckon Functions

Certain syntaxes of the distance and reckon functions use angles to denote distances in the way described above. In the following statements, the range argument, arclen, is in degrees (along with all the other inputs and outputs):

```
[arclen, az] = distance(lat1, lon1, lat2, lon2)
[latout, lonout] = reckon(lat, lon, arclen, az)
```

By adding the optional units argument, you can use radians instead:

```
[arclen, az] = distance(lat1, lon1, lat2, lon2, 'radians')
[latout, lonout] = reckon(lat, lon, arclen, az, 'radians')
```

If an ellipsoid argument is provided, however, then arclen has units of length, and they match the units of the semimajor axis length of the reference ellipsoid. If you specify ellipsoid = [1 0] (the unit sphere), arclen can be considered to be either an angle in radians or a length defined in units of earth radii. It has the same value either way. Thus, in the following computation, lat1, lon1, lat2, lon2, and az are in degrees, but arclen will appear to be in radians:

```
[arclen, az] = distance(lat1, lon1, lat2, lon2, [1 0])
```

Summary: Available Distance and Angle Conversion Functions

The following table shows the Mapping Toolbox unit-to-unit distance and arc conversion functions. They all accept scalar, vector, and higher-dimension inputs. The first two columns and rows involve angle units, the last three involve distance units:

Functions that Directly Convert Angles, Lengths, and Spherical Distances

Convert	To Degrees	To Radians	To Kilometers	To Nautical Miles	To Statute Miles
Degrees	toDegrees fromDegrees	deg2rad toRadians fromDegrees	deg2km	deg2nm	deg2sm
Radians	rad2deg toDegrees fromRadians	toRadians fromRadians	rad2km	rad2nm	rad2sm
Kilometers	km2deg	km2rad		km2nm	km2sm
Nautical Miles	nm2deg	nm2rad	nm2km		nm2sm
Statute Miles	sm2deg	sm2rad	sm2km	sm2nm	

The angle conversion functions along the major diagonal, toDegrees, toRadians, fromDegrees, and fromRadians, can have no-op results. They are intended for use in applications that have no prior knowledge of what angle units might be input or desired as output.

Great Circles

In plane geometry, lines have two important characteristics. A line represents the shortest path between two points, and the slope of such a line is constant. When describing lines on the surface of a spheroid, however, only one of these characteristics can be guaranteed at a time.

A great circle is the shortest path between two points along the surface of a sphere. The precise definition of a great circle is the intersection of the surface with a plane passing through the center of the planet. Thus, great circles always bisect the sphere. The equator and all meridians are great circles. All great circles other than these do not have a constant azimuth, the spherical analog of slope; they cross successive meridians at different angles. That great circles are the shortest path between points is not always apparent from maps, because very few map projections (the Gnomonic is one of them) represent arbitrary great circles as straight lines.

Because they define paths that minimize distance between two (or three) points, great circles are examples of geodesics. In general, a geodesic is the straightest possible path constrained to lie on a curved surface, independent of the choice of a coordinate system. The term comes from the Greek *geo-*, earth, plus *daiesthai*, to divide, which is also the root word of *geodesy*, the science of describing the size and shape of the Earth mathematically.


For more information, see "Generate Vector Data for Points Along Great Circle or Rhumb Line Tracks" on page 3-29.

Rhumb Lines

A rhumb line is a curve that crosses each meridian at the same angle. This curve is also referred to as a loxodrome (from the Greek *loxos*, slanted, and *drome*, path). Although a great circle is a shortest path, it is difficult to navigate because your bearing (or azimuth) continuously changes as you proceed. Following a rhumb line covers more distance than following a geodesic, but it is easier to navigate.

All parallels, including the equator, are rhumb lines, since they cross all meridians at 90°. Additionally, all meridians are rhumb lines, in addition to being great circles. A rhumb line always spirals toward one of the poles, unless its azimuth is true east, west, north, or south, in which case the rhumb line closes on itself to form a parallel of latitude (small circle) or a pair of antipodal meridians.

The following figure depicts a great circle and one possible rhumb line connecting two distant locations. For information about how to calculate points along great circles and rhumb lines, see "Generate Vector Data for Points Along Great Circle or Rhumb Line Tracks" on page 3-29.



Azimuth

Azimuth is the angle a line makes with a meridian, measured clockwise from north. Thus the azimuth of due north is 0° , due east is 90° , due south is 180° , and due west is 270° . You can instruct several Mapping Toolbox functions to compute azimuths for any pair of point locations, either along rhumb lines or along great circles. These will have different results except along cardinal directions. For great circles, the result is the azimuth at the initial point of the pair defining a great circle path. This is because great circle azimuths other than 0° , 90° , 180° , and 270° do not remain constant. Azimuths for rhumb lines are constant along their entire path (by definition).

For rhumb lines, computing an azimuth backward (from the second point to the first) yields the complement of the forward azimuth ($(Az + 180^{\circ}) \mod 360^{\circ}$). For great circles, the back azimuth is generally not the complement, and the difference depends on the distance between the two points.

In addition to forward and back azimuths, Mapping Toolbox functions can compute locations of points a given distance and azimuth from a reference point, and can calculate tracks to connect waypoints, along either great circles or rhumb lines on a sphere or ellipsoid.

For more an example that uses azimuths, see "Reckoning" on page 3-31

Calculate Azimuth

When the azimuth is calculated from one point to another using the toolbox, the result depends upon whether you want a great circle or a rhumb line azimuth. For great circles, the result is the azimuth at the starting point of the connecting great circle path. In general, the azimuth along a great circle is not constant. For rhumb lines, the resulting azimuth is constant along the entire path.

Azimuths, or bearings, are returned in the same angular units as the input latitudes and longitudes. The default path type is the shorter great circle, and the default angular units are degrees. In the example, the great circle azimuth from the first point to the second is

One feature of rhumb lines is that the inverse azimuth, from the second point to the first, is the complement of the forward azimuth and can be calculated by simply adding 180° to the forward value:

The azimuths associated with cardinal and intercardinal compass directions are the following:

North	0° or 360°
Northeast	45°
East	90°
Southeast	135°
South	180°
Southwest	225°
West	270°
Northwest	315°

Elevation

Elevation is the angle above the local horizontal of one point relative to the other. To compute the elevation angle of a second point as viewed from the first, provide the position and altitude of the points. The default units are degrees for latitudes and longitudes and meters for altitudes, but you can specify other units for each.

What are the elevation, slant range, and azimuth of a point 10 kilometers east and 10 kilometers above a surface point?

On an ellipsoid, azimuths returned from <code>geodetic2aer</code> generally will differ from those returned by <code>azimuth</code> and <code>distance</code>.


See Also

geodetic2aer

Generate Vector Data for Points Along Great Circle or Rhumb Line Tracks


You can generate vector data corresponding to points along great circle or rhumb line tracks using the track1 and track2 functions. If you have a point on the track and an azimuth at that point, use track1. If you have two points on the track, use track2. For example, to get the great circle path starting at (31°S, 90°E) with an azimuth of 45° with a length of 12°, use track1:

For the great circle from (31°S, 90°E) to (23°S, 110°E), use track2:



The track1 function also allows you to specify range endpoints. For example, if you want points along a rhumb line starting 5° away from the initial point and ending 13° away, at an azimuth of 55°, simply specify the range limits:

track1 with range limits



When no range is provided for track1, the returned points represent a *complete track*. For great circles, a complete track is 360°, encircling the planet and returning to the initial point. For rhumb lines, the complete track terminates at the poles, unless the azimuth is 90° or 270°, in which case the complete track is a parallel that returns to the initial point.

For calculated tracks, 100 points are returned unless otherwise specified. You can calculate several tracks at one time by providing vector inputs. For more information, see the track1 and track2

reference pages. For more information about rhumb lines, see "Rhumb Lines" on page 3-25. For more information about great circles, see "Great Circles" on page 3-24. More vector path calculations are described in "Navigation" on page 10-9.

Reckoning

A common problem in geographic applications is the determination of a destination given a starting point, an initial azimuth, and a distance. In the toolbox, this process is called reckoning. A new position can be reckoned in a great circle or a rhumb line sense (great circle or rhumb line track).

As an example, an airplane takes off from La Guardia Airport in New York (40.75°N, 73.9°W) and follows a northwestern rhumb line flight path at 200 knots (nautical miles per hour). Where would it be after 1 hour?

Notice that the distance, 200 nautical miles, must be converted to degrees of arc length with the nm2deg conversion function to match the latitude and longitude inputs. If the airplane had a flight computer that allowed it to follow an exact great circle path, what would the aircraft's new location be?

Notice also that for short distances at these latitudes, the result hardly differs between great circle and rhumb line. The two destination points are less than 4 nautical miles apart. Incidentally, after 1 hour, the airplane would be just north of New York's Finger Lakes.

See Also

More About

- "Rhumb Lines" on page 3-25
- "Great Circles" on page 3-24

Calculate Distance Between Two Points in Geographic Space

When Mapping Toolbox functions calculate the distance between two points in geographic space, the result depends upon whether you specify great circle or rhumb line distance. The distance function returns the appropriate distance between two points as an angular arc length, employing the same angular units as the input latitudes and longitudes. The default path type is the shorter great circle, and the default angular units are degrees. The previous figure shows two points at (15°S, 0°) and (60°N, 150°E). The great circle distance between them, in degrees of arc, is as follows:

To determine how much longer the rhumb line path is in, say, kilometers, you can use a distance conversion function on the difference:

```
kmdifference = deg2km(distrh-distgc)
kmdifference =
    1.6744e+03
```

Several distance conversion functions are available in the toolbox, supporting degrees, radians, kilometers, meters, statute miles, nautical miles, and feet. Converting distances between angular arc length units and surface length units requires the radius of a planet or spheroid. By default, the radius of the Earth is used.

Generate Small Circles

A small circle is the intersection of a plane with the surface of a sphere, such as a parallel of latitude on a spherical representation of the Earth. You can generate a small circle from the center point and a point on the perimeter by using the scircle2 function. You can generate a small circle from the center point and the arc length of the radius by using the scircle1 function.

For this example, create a small circle that surrounds Norway, Sweden, and Finland by using the scircle2 function and then create an identical small circle by using the scircle1 function.

First, specify the coordinates of a center point and a point along the perimeter. Find the coordinates of 100 points that make up the small circle by using the scircle2 function.

```
centerLat = 62;
centerLon = 20;
perimeterLat = 72;
perimeterLon = 19;
[lat2,lon2] = scircle2(centerLat,centerLon, ...
    perimeterLat,perimeterLon);
```

Calculate the arc length in degrees between the center point and the point along the perimeter. Find the coordinates of the same small circle by using the scircle1 function.

```
[arclen,~] = distance(centerLat,centerLon, ...
    perimeterLat,perimeterLon);
[lat1,lon1] = scircle1(centerLat,centerLon,arclen);
```

Verify that the small circles are identical, within a tolerance.

```
dLat = abs(lat1-lat2);
dLon = abs(lon1-lon2);
all(dLat < le-12)
ans = logical
    1

all(dLon < le-12)
ans = logical
    1</pre>
```

Display the center point, perimeter point, and small circle on the surface of a geographic globe. Change the view by using the campos function.


```
uif = uifigure;
g = geoglobe(uif,'Terrain','none');
hold(g,'on')
geoplot3(g,centerLat,centerLon,0,'ro','LineWidth',2)
geoplot3(g,perimeterLat,perimeterLon,0,'ro','LineWidth',2)
geoplot3(g,lat1,lon1,0,'r','LineWidth',2)
campos(g,40,-18,10000000)
```



See Also scircle1|scircle2

Measure Area of Spherical Quadrangles

In solid geometry, the area of a spherical quadrangle can be exactly calculated. A spherical quadrangle is the intersection of a *lune* and a *zone*. In geographic terms, a *quadrangle* is defined as a region bounded by parallels north and south, and meridians east and west.



In the pictured example, a quadrangle is formed by the intersection of a zone, which is the region bounded by 15°N and 45°N latitudes, and a lune, which is the region bounded by 0° and 30°E longitude. Under the spherical planet assumption, the fraction of the entire spherical surface area inscribed in the quadrangle can be calculated:

```
area = areaquad(15,0,45,30)
area =
     0.0187
```

That is, less than 2% of the planet's surface area is in this quadrangle. To get an absolute figure in, for example, square miles, you must provide the appropriate spherical radius. The radius of the Earth is about 3958.9 miles:

```
area = areaquad(15,0,45,30,3958.9)
area = 3.6788e+06
```

The surface area within this quadrangle is over 3.6 million square miles for a spherical Earth.

Plotting a 3-D Dome as a Mesh over a Globe

This example shows how to start with a 3-D feature in a system of local east-north-up (ENU) coordinates, then transform and combine it with a globe display in Earth-Centered, Earth-Fixed (ECEF) coordinates.

Step 1: Set Defining Parameters

Use Geodetic Reference System 1980 (GRS80) and work in units of kilometers. Place the origin of the local system near Washington, DC, USA.

```
grs80 = referenceEllipsoid("grs80","km");
domeRadius = 3000; % km
domeLat = 39; % degrees
domeLon = -77; % degrees
domeAlt = 0: % km
```


Step 2: Construct the Dome in Local East-North-Up Coordinates

The local ENU system is defined with respect to a geodetic reference point, specified in this case by (domeLat, domeLon, and domeAlt). It is a 3-D Cartesian system in which the positive x-axis is directed to the east, the positive y-axis is directed to the north, and the z-axis is normal to the reference ellipsoid and directed upward.

In this example, the 3-D feature is a hemisphere in the z>=0 half-space with a radius of 3000 kilometers. This hemisphere could enclose, hypothetically, the volume of space within range of a idealized radar system having uniform coverage from the horizon to the zenith, in all azimuths. Volumes of space such as this, when representing zones of effective surveillance coverage, are sometimes known informally as "radar domes."


A quick way to construct coordinate arrays outlining a closed hemispheric dome is to start with a unit sphere, scale up the radius, and collapse the lower hemisphere. It's easier to visualize if you make it semitransparent -- setting the FaceAlpha to 0.5 in this case.

```
[x,y,z] = sphere(20);
xEast = domeRadius * x;
yNorth = domeRadius * y;
zUp = domeRadius * z;
zUp(zUp < 0) = 0;
surf(xEast,yNorth,zUp,"FaceColor","yellow","FaceAlpha",0.5)
axis equal</pre>
```



Step 3: Convert Dome to the Earth-Centered Earth-Fixed (ECEF) System


Use the enu2ecef function to convert the dome from local ENU to an ECEF system, based on the GRS 80 reference ellipsoid. It applies a 3-D translation and rotation. Notice how the hemisphere becomes tilted and how its center moves thousands of kilometers from the origin.



Step 4: Construct a Globe Display

Construct a basic globe display using axesm and globe.

```
figure
ax = axesm("globe", "Geoid", grs80, "Grid", "on", ...
    "GLineWidth",1, "GLineStyle", "-",...
    "Gcolor",[0.9 0.9 0.1], "Galtitude",100);
ax.Position = [0 0 1 1];
axis equal off
view(3)
```



Step 5: Add Various Global Map Data

Add low-resolution global topography, coastlines, and rivers to the globe.

```
load topo60c
geoshow(topo60c,topo60cR,"DisplayType","texturemap")
demcmap(topo60c)

load coastlines
geoshow(coastlat,coastlon,"Color","black")


rivers = readgeotable("worldrivers.shp");
geoshow(rivers,"Color","blue")
```



Step 6: Add the Dome to the Globe Display

Add the ECEF version of dome to the globe axes as a semitransparent mesh.

surf(xECEF,yECEF,"FaceColor","yellow","FaceAlpha",0.5)



You can view the dome and globe from different angles by interactively rotating the axes.

Credit

Thanks to Edward J. Mayhew, Jr. for providing technical background on "radar domes" and for bringing to our attention the problem of visualizing them with the Mapping Toolbox $^{\text{\tiny M}}$.

Comparison of 3-D Coordinate Systems

Coordinate systems represent position on the Earth using coordinates. Mapping Toolbox functions transform coordinates between Earth-centered Earth-fixed (ECEF), geodetic, east-north-up (ENU), north-east-down (NED), and azimuth-elevation-range (AER) systems.


Global systems such as ECEF and geodetic systems describe the position of an object using a triplet of coordinates. Local systems such as ENU, NED, and AER systems require two triplets of coordinates: one triplet describes the location of the origin, and the other triplet describes the location of the object with respect to the origin.

When you work with 3-D coordinate systems, you must specify an ellipsoid model that approximates the shape of the Earth. For more information about ellipsoid models, see "Reference Spheroids" on page 3-4. All of the sample coordinates on this page use the World Geodetic System of 1984 (WGS84).

Earth-Centered Earth-Fixed Coordinates

An Earth-centered Earth-fixed (ECEF) system uses the Cartesian coordinates (X,Y,Z) to represent position relative to the center of the reference ellipsoid. The distance between the center of the ellipsoid and the center of the Earth depends on the reference ellipsoid.

- The positive *X*-axis intersects the surface of the ellipsoid at 0° latitude and 0° longitude, where the equator meets the prime meridian.
- The positive Y-axis intersects the surface of the ellipsoid at 0° latitude and 90° longitude.
- The positive Z-axis intersects the surface of the ellipsoid at 90° latitude and 0° longitude, the North Pole.




For example, the ECEF coordinates of Parc des Buttes-Chaumont are (4198945 m, 174747 m, 4781887 m).


Geodetic Coordinates

A geodetic system uses the coordinates (*lat,lon,h*) to represent position relative to a reference ellipsoid.


• *lat*, the latitude, originates at the equator. More specifically, the latitude of a point is the angle a normal to the ellipsoid at that point makes with the equatorial plane, which contains the center and equator of the ellipsoid. An angle of latitude is within the range [-90°, 90°]. Positive latitudes correspond to north and negative latitudes correspond to south.



• *lon*, the longitude, originates at the prime meridian. More specifically, the longitude of a point is the angle that a plane containing the ellipsoid center and the meridian containing that point makes with the plane containing the ellipsoid center and prime meridian. Positive longitudes are measured in a counterclockwise direction from a vantage point above the North Pole. Typically, longitude is within the range [-180°, 180°] or [0°, 360°].



h, the ellipsoidal height, is measured along a normal of the reference spheroid. Coordinate transformation functions such as geodetic2ecef require you to specify h in the same units as the reference ellipsoid. You can change the units of the reference ellipsoid using the LengthUnit property. Terrain models typically supply data using orthometric height rather than ellipsoidal height. For information about calculating ellipsoidal height from orthometric height, see "Find Ellipsoidal Height from Orthometric and Geoid Height" on page 3-51.




For example, the geodetic coordinates of Parc des Buttes-Chaumont are (48.8800°, 2.3831°, 124.5089 m).

East-North-Up Coordinates

An east-north-up (ENU) system uses the Cartesian coordinates (xEast,yNorth,zUp) to represent position relative to a local origin. The local origin is described by the geodetic coordinates (lat0,lon0,h0). Note that the origin does not necessarily lie on the surface of the ellipsoid.

- The positive *xEast*-axis points east along the parallel of latitude containing *lat0*.
- The positive *yNorth*-axis points north along the meridian of longitude containing *lon0*.
- The positive *zUp*-axis points upward along the ellipsoid normal.




For example, Montmartre has geodetic coordinates (48.8862°, 2.3343°, 174.5217 m). The ENU coordinates of Parc des Buttes-Chaumont with respect to Montmartre are (3579.4232 m, -688.3514 m, -51.0524 m).

North-East-Down Coordinates

A north-east-down (NED) system uses the Cartesian coordinates (xNorth,yEast,zDown) to represent position relative to a local origin. The local origin is described by the geodetic coordinates (lat0,lon0,h0). Typically, the local origin of an NED system is above the surface of the Earth.

- The positive *xNorth*-axis points north along the meridian of longitude containing *lon0*.
- The positive *yEast*-axis points east along the parallel of latitude containing *lat0*.
- The positive *zDown*-axis points downward along the ellipsoid normal.




An NED coordinate system is commonly used to specify location relative to a moving aircraft. In this application, the origin and axes of an NED system change continuously. Note that the coordinates are not fixed to the frame of the aircraft.

For example, an aircraft flying into Charles de Gaulle airport has geodetic coordinates (48.9978°, 2.7594°, 699.8683 m). The NED coordinates of the airport with respect to the plane are (1645.8313 m, -15677.1868 m, 555.8221 m).

Azimuth-Elevation-Range Coordinates

An azimuth-elevation-range (AER) system uses the spherical coordinates (*az,elev,range*) to represent position relative to a local origin. The local origin is described by the geodetic coordinates (*lat0,lon0,h0*). Azimuth, elevation, and slant range are dependent on a local Cartesian system, for example, an ENU system.

- *az*, the azimuth, is the clockwise angle in the *xEast-yNorth* plane from the positive *yNorth*-axis to the projection of the object into the plane.
- *elev*, the elevation, is the angle from the *xEast-yNorth* plane to the object.
- range, the slant range, is the Euclidean distance between the object and the local origin.



For example, a lidar sensor at the Charles de Gaulle airport has geodetic coordinates (48.0124° , 2.5451° , 163.4885 m). The AER coordinates of an airplane with respect to the sensor are (95.8314° , 1.8781° , 15773.1381 m).

Tips

If you are transforming coordinates between ENU, NED, and AER systems with the same origin, then you do not need to specify a reference ellipsoid or the coordinates of the origin.

See Also

geodetic2ecef | ecef2enu | enu2aer | aer2ned | ned2geodetic | geodetic2aer

More About

• "Reference Spheroids" on page 3-4

References

[1] Guowei, C., B.M. Cheh, and T. H. Lee. *Unmanned Rotorcraft Systems*. London: Springer-Verlag London Limited: 2011.


[2] Van Sickle, J. Basic GIS Coordinates. Boca Raton, FL: CRC Press LLC, 2004.

Vectors in 3-D Coordinate Systems


Vectors represent quantities such as velocity and acceleration. Mapping Toolbox functions transform vector components between Earth-centered Earth-fixed (ECEF) and east-north-up (ENU) or north-east-down (NED) systems. For more information about ECEF, ENU, and NED coordinate systems, see "Comparison of 3-D Coordinate Systems" on page 3-42.

Unlike coordinates that measure position, vector components in a Cartesian system do not depend on a position in space. Therefore, when you transform a vector from one system to another, only the components of the vector change. The magnitude of the vector remains the same.


For example, this image shows a 2-D vector transformation from an x-y system to a u-v system. The vector has components x = 2 and y = 1 in the x-y system, and components u = 1.30 and v = 1.82 in the u-v system. The components of the vector are different, but in each system the magnitude of the vector is 2.24 units.



This image shows a coordinate transformation from a global ECEF system to a local ENU system using ecef2enu. The position vectors start at the origin of each system and end at point P. Therefore, the transformation changes the magnitude of the position vector.



This image shows a vector transformation from a global ECEF system to a local ENU system using ecef2enuv. The vector \mathbf{r} does not depend on a position. Therefore, the transformation changes the components of the vector, but the magnitude of the vector is the same.



Tips

Unlike coordinate transformation functions such as ecef2enu, vector transformation functions such as ecef2enuv do not require you to specify a reference spheroid or the ellipsoidal height of the local origin. The geodetic latitude and longitude of the local origin is sufficient to define the orientation of the uEast, vNorth, and wUp axes.

See Also

enu2ecefv | ned2ecefv | ecef2nedv | ecef2enuv


More About

• "Comparison of 3-D Coordinate Systems" on page 3-42

Find Ellipsoidal Height from Orthometric Height

The *height* of an object may refer to its ellipsoidal height or its orthometric height. Mapping Toolbox functions such as <code>geodetic2enu</code> require the input argument *ellipsoidal height*, but data often quantifies *orthometric height* instead. You can convert orthometric height to ellipsoidal height by using a geoid model.


Ellipsoidal height, called h, is height measured along a normal of a reference ellipsoid. For more information about reference ellipsoids, see "Reference Spheroids" on page 3-4. This image shows a positive ellipsoidal height, h_p , and a negative ellipsoidal height, h_p .



Most terrain models provide data using orthometric height instead of ellipsoidal height. Orthometric height, called H, is height above the geoid.

The *geoid* models the average sea level of the Earth without effects such as weather, tides, and land. A geoid model is created by measuring variations in the Earth's gravitational field, so it has a smoothly undulating shape. Orthometric height is measured relative to the geoid.


Geoid height, called N, is the height of the geoid measured along a normal of a reference ellipsoid. For example, geoid height values from the Earth Gravitational Model of 1996 (EGM96) are referenced to the ellipsoid defined by the World Geodetic System of 1984 (WGS84). Below is an illustration of the geoid from EGM96, with geoid heights in meters.



To find ellipsoidal height at a specified latitude and longitude, add the orthometric height and geoid height: h = H + N. You can find the height of the geoid from EGM96 at specified latitudes and longitudes using the egm96geoid function.

The equation h = H + N is an approximation because the direction along which a geoid height is measured is not necessarily the same as the direction along which an orthometric height is measured. However, the approximation is suitable for most practical purposes.

The following image illustrates the relationship between ellipsoidal height, orthometric height, and the geoid. The values h_1 , H_1 , and N_1 demonstrate the relationship for an airborne object, while h_2 , H_2 , and N_2 demonstrate the relationship for an object on land.



Find Ellipsoidal Height from Orthometric and Geoid Height

Find the ellipsoidal height of the summit of Mount Everest, using its orthometric height and a geoid model.

Specify the latitude and longitude of the summit in degrees. Specify the orthometric height in meters.

```
lat = 27.988056;
lon = 86.925278;
H = 8848;
```

Find the height of the geoid at the location specified by lat and lon using egm96geoid.

```
N = egm96geoid(lat,lon);
```

Calculate the ellipsoidal height of the summit.

```
h = H + N
h = 8.8193e+03
```

References

[1] NOAA. "What is the geoid?" *National Ocean Service website*. https://oceanservice.noaa.gov/facts/geoid.html, 06/25/18.

See Also

egm96geoid|geodetic2enu

More About

• "Reference Spheroids" on page 3-4

Creating and Viewing Maps

- "Introduction to Mapping Graphics" on page 4-2
- "Continent, Country, Region, and State Maps Made Easy" on page 4-3
- "Set Background Colors for Map Displays" on page 4-4
- "Create Simple Maps Using worldmap" on page 4-5
- "Create Simple Maps Using usamap" on page 4-7
- "axesm-Based Maps" on page 4-10
- "Map Limit Properties" on page 4-12
- "Switch Between Projections" on page 4-27
- "Reprojection of Graphics Objects" on page 4-34
- "Change Map Projections Using geoshow" on page 4-37
- "The Map Frame" on page 4-41
- "Map and Frame Limits" on page 4-43
- "The Map Grid" on page 4-44
- "Summary of Polygon Display Functions" on page 4-47
- "Display Vector Data as Points and Lines" on page 4-49
- "Display Vector Data as Lines and Patches" on page 4-52
- "Types of Data Grids and Raster Display Functions" on page 4-58
- "Fit Gridded Data to the Graticule" on page 4-59
- "Create 3-D Displays with Raster Data" on page 4-63
- "Create Map Displays with Geographic Data" on page 4-66
- "Create Maps with Data in Projected Coordinate Reference Systems" on page 4-76
- "Pick Locations Interactively" on page 4-85
- "Create an Interactive Map for Selecting Point Features" on page 4-87
- "Create Small Circle and Track Annotations on Maps Interactively" on page 4-93
- "Interactively Display Text Annotations on a Map" on page 4-95
- "Work with Objects by Name" on page 4-96

Introduction to Mapping Graphics

Even though geospatial data often is manipulated and analyzed without being displayed, high-quality interactive cartographic displays can play valuable roles in exploratory data analysis, application development, and presentation of results.

Using Mapping Toolbox capabilities, you can display geographic information almost as easily as you can display tabular or time-series data in MATLAB plots. Most mapping functions are similar to MATLAB plotting functions, except they accept data with geographic/geodetic coordinates (latitudes and longitudes) instead of Cartesian and polar coordinates. Mapping functions typically have the same names as their MATLAB counterparts, with the addition of an 'm' suffix (for maps). For example, the Mapping Toolbox analog to the MATLAB plot function is plotm.

Mapping Toolbox software manages most of the details in displaying a map. It projects your data, cuts and trims it to specified limits, and displays the resulting map at various scales. With the toolbox you can also add customary cartographic elements, such as a frame, grid lines, coordinate labels, and text labels, to your displayed map. If you change your projection properties, or even the projection itself, some Mapping Toolbox map displays are automatically redrawn with the new settings, undoing any cuts or trims if necessary.

The toolbox also makes it easy to modify and manipulate maps. You can modify the map display and mapped objects either from the command line or through property editing tools you can invoke by clicking on the display.

Note In its current implementation, the toolbox maintains the map projection and display properties by storing special data in the UserData property of the axesm-based map. The toolbox also takes over the UserData property of objects projected on axesm-based maps. Therefore, never attempt to set the UserData property of an axesm-based map or an object projected onto an axesm-based map. Do not apply the MATLAB get function to axes UserData, depend on the contents of UserData in any way, or apply functions that set or get UserData to the axesm-based map or the objects mapped on an axesm-based map. Only use the Mapping Toolbox functions getm and setm to obtain and modify the properties of axesm-based maps.

Continent, Country, Region, and State Maps Made Easy

Mapping Toolbox functions axesm and setm enable you to control the full range of properties when constructing a projected axesm-based map. Functions worldmap and usamap, on the other hand, trade control for simplicity and convenience. These two functions each create an axesm-based map that is suitable for a country or region of the world or the United States, automatically selecting the map projection, limits, and other properties based on the name of the area you want to map. Once you have jump-started your map with worldmap or usamap, you are ready to add your data, using geoshow or any of the lower level geographic data display functions. Optionally, you can use the axesm-based map created by worldmap or usamap as a starting point, and then customize it by adjusting selected properties with setm.

Set Background Colors for Map Displays

If you prefer that your maps have white backgrounds instead, you can create figures with the command

```
figure('Color','white')
```

If you want a custom background color, specify a color triplet in place of white. For example, to make a beige background, type

```
figure('Color',[.95 .9 .8])
```

To give a white background to an existing figure, type

```
set(gca,'color','white')
```

If you want all figures in a session to have white backgrounds, set this as a default with the command

```
set(0, 'DefaultFigureColor', 'white');
```

To avoid having to do this every time you start MATLAB, place this command in your startup.m file.


You can also use the Property Editor, part of the MATLAB plotting tools, to modify background colors for figures and axes.

Create Simple Maps Using worldmap

This example shows how to create simple axesm-based maps by using the worldmap function.

Set up the map frame, letting the worldmap function pick the projection. This example creates a map of South America.

```
worldmap 'south america'
axis off
```




Determine which map projection the worldmap function used by looking at the value of the MapProjection property of the axesm-based map. The value eqdconic stands for Equidistant Conic projection

```
getm(gca,'MapProjection')
ans =
'eqdconic'
```

Use the geoshow function to import sample data for land areas, major rivers, and major cities from shapefiles and display it using color you specify.

```
geoshow('landareas.shp','FaceColor',[0.5 0.7 0.5])
geoshow('worldrivers.shp','Color', 'blue')
geoshow('worldcities.shp','Marker','.','Color','red')
```




Create Simple Maps Using usamap

This example shows how to create axesm-based maps of the United States by using the usamap function. The usamap function lets you make maps of the United States as a whole, just the conterminous portion (the "lower 48" states), groups of states, or a single state. The map you create with the usamap function has a labelled grid fitted around the area you specify but contains no data, allowing you to generate the kind of map you want using display functions such as the geoshow function.

Specify map limits and set up an axesm-based map. This example creates a map of the Chesapeake Bay region.

```
latlim = [37 40];
lonlim = [-78 -74];
figure
ax = usamap(latlim,lonlim);
axis off
```



Determine the map projection used by the usamap function. The Lambert Conformal Conic projection is often used for maps of the conterminous United States.

```
getm(gca,'MapProjection')
ans =
'lambert'
```


Use the readgeotable function to read U.S. state polygon boundaries from the shapefile called usastatehi.shp. The function returns the data in a geospatial table.

```
states = readgeotable('usastatehi.shp');
```

Create a symbol specification to create a political map using the pol cmap function.

Display the filled polygons by using the geoshow function.


```
geoshow(states,'SymbolSpec',faceColors)
```



Extract the names for states within the map limits and use the textm function to plot them at the label points provided by the geospatial table. Because polcmap assigns random pastel colors to patches, your map might look different than this example.

```
for k = 1:h
    labelPointIsWithinLimits = ...
    latlim(1) < states.LabelLat(k) &&...
    latlim(2) > states.LabelLat(k) &&...
    lonlim(1) < states.LabelLon(k) &&...
    lonlim(2) > states.LabelLon(k);
if labelPointIsWithinLimits
    textm(states.LabelLat(k),...
    states.LabelLon(k), states.Name(k),...
```

```
'HorizontalAlignment','center')
end
end
textm(38.2,-76.1,' Chesapeake Bay ',...
'fontweight','bold','Rotation',270)
```



axesm-Based Maps

When you create a map, you can use one of the Mapping Toolbox built-in user interfaces (UIs), or you can build the graphic with MATLAB and Mapping Toolbox functions. Many MATLAB graphics are built using the axes function:

```
axes
axes('PropertyName',PropertyValue,...)
axes(h)
h = axes(...)
```

Mapping Toolbox functions include an extended version of the axes function, called the axesm function. Maps created with the axesm function, called axesm-based maps (previously referred to as map axes) share all properties associated with regular axes, and they include information about the current coordinate system (map projection), as well as data to define the map grid and its labeling, the map frame and its limits, scale, and other properties. For complete descriptions of all axesm-based map properties, see the axesm-Based Map Properties reference page.

The syntax of axesm is similar to that of axes:

```
axesm
axesm(PropertyName,PropertyValue,...)
axesm(ProjectionFcn,PropertyName,PropertyValue,...)
```

The axesm function without arguments brings up a UI that lists all supported projections and assists in defining their parameters. You can also summon this UI with the axesmui function once you have created an axesm-based map.

The figure window created using axesm contains the same set of tools and menus as any MATLAB figure. By default, the figure window is blank, even if there is map data in your workspace. You can toggle certain properties, such as grids, frames, and axis labels, by right-clicking in the figure window to obtain a pop-up menu.

Tips to Working with axesm-Based Maps

- You can list all the names, classes, and IDs of map projections supported by axesm-based maps with the maps function.
- You can place many types of objects in an axesm-based map, such as lines, patches, markers, scale rulers, north arrows, grids, and text. You can use the handlem function and its associated UI to list these objects. See the handlem reference page for a list of the objects that can occupy an axesm-based map and how to query for them.
- You can define multiple independent figures containing axesm-based maps, but only one can be active at any one time. Use axes(obj) to activate an existing axesm-based map.
- axesm-based maps created by axesm contain projection information in a structure. For an example of what these properties are, type

```
h = axesm('MapProjection','mercator')
```

and then use the getm function to retrieve all the axesm-based map properties:

```
p = getm(h)
```

See Also

axesm|axesmui|handlem

Map Limit Properties

In many common situations, the map limit properties of axesm-based maps, MapLatLimit and MapLonLimit, provide a convenient way of specifying your map projection origin or frame limits. Note that these properties are intentionally redundant; you can always avoid them if you wish and instead use the Origin, FLatLimit, and FLonLimit properties to set up your map. When they're applicable, however, you'll probably find that it's easier and more intuitive to set MapLatLimit and MapLonLimit, especially when creating a new axesm-based map.

You typically use the MapLatLimit and MapLonLimit properties to set up an axesm-based map with a non-oblique, non-azimuthal projection, with its origin on the Equator. (Most of the projections included in the Mapping Toolbox fall into this category; e.g., cylindrical, pseudo-cylindrical, conic, or modified azimuthal.) In addition, even with a non-zero origin latitude (origin off the Equator), you can use the MapLatLimit and MapLonLimit properties with projections that are implemented directly rather than via rotations of the sphere (e.g., tranmerc, utm, lambertstd, cassinistd, eqaconicstd, eqdconicstd, and polyconicstd). This list includes the projections used most frequently for large-scale maps, such as U.S. Geological Survey topographic quadrangle maps. Finally, when the origin is located at a pole or on the Equator, you can use the map limit properties with any azimuthal projection (e.g., stereo, ortho, breusing, eqaazim, eqdazim, gnomonic, or vperspec).

On the other hand, you should avoid the map limit properties, working instead with the Origin, FLatLimit, and FLonLimit properties, when:

- You want your map frame to be positioned asymmetrically with respect to the origin longitude.
- You want to use an oblique aspect (that is, assign a non-zero rotation angle to the third element of the "orientation vector" supplied as the Origin property value).
- You want to change your projection's default aspect (normal vs. transverse).
- You want to use a nonzero origin latitude, except in one of the special cases noted above.
- You are using one of the following projections:
 - globe No need for map limits; always covers entire planet
 - cassini Always in a transverse aspect
 - wetch Always in a transverse aspect
 - bries Always in an oblique aspect

There's no need to supply a value for the MapLatLimit property if you've already supplied one for the Origin and FLatLimit properties. In fact, if you supply all three when calling either axesm or setm, the FLatLimit value will be ignored. Likewise, if you supply values for Origin, FLonLimit, and MapLonLimit, the FLonLimit value will be ignored.

If you do supply a value for either MapLatLimit or MapLonLimit in one of the situations listed above, axesm or setm will ignore it and issue a warning. For example,

```
axesm('lambert','Origin',[40 0],'MapLatLimit',[20 70])
```

generates the warning message:

Ignoring value of MapLatLimit due to use of nonzero origin latitude with the lambert projection.

It's important to understand that MapLatLimit and MapLonLimit are extra, redundant properties that are coupled to the Origin, FLatLimit, and FLonLimit properties. On the other hand, it's not too difficult to know how to update your axesm-based map if you keep in mind the following:

- The Origin property takes precedence. It is set (implicitly, if not explicitly) every time you call axesm and you cannot change it just by changing the map limits. (Note that when creating a new axesm-based map, the map limits are used to help set the origin if it is not explicitly specified.)
- MapLatLimit takes precedence over FLatLimit if both are provided in the same call to axesm or setm, but changing either one alone affects the other.
- MapLonLimit and FLonLimit have a similar relationship.

The precedence of Origin means that if you want to reset your map limits with setm and have setm also determine a new origin, you must set Origin to [] in the same call. For example,

```
setm(gca,'Origin',[],'MapLatLimit',newMapLatlim,...
'MapLonLimit',newMapLonlim)
```

On the other hand, a call like this will automatically update the values of FLatLimit and FLonLimit. Similarly, a call like:

```
setm(gca,'FLatLimit',newFrameLatlim,'FLonLimit',newFrameLonlim)
```

will update the values of MapLatLimit and MapLonLimit.

Finally, you probably don't want to try the following:

```
setm(gca, 'Origin',[], 'FLonLimit', newFrameLonlim)
```


because the value of FLonLimit (unlike MapLonLimit) will not affect Origin, which will merely change to a projection-dependent default value (typically $[0 \ 0]$).

Specify Map Projection Origin and Frame Limits Automatically

This example shows how to specify the map projection origin and frame limits of axesm-based maps using the two map limit properties: MapLatLimit and MapLonLimit. While axesm-based maps support properties to set these values directly, Origin, FLatLimit, and FLonLimit, it is easier and more intuitive to use the map limit properties, especially when creating a new axesm-based map. This example highlights the interdependency of the axesm-based map limits and the map limit properties.

Create a map using a cylindrical projection or pseudo-cylindrical projection showing all or most of the Earth, with the Equator running as a straight horizontal line across the center of the map. The map is bounded by a geographic quadrangle and the projection origin is located on the Equator, centered between the longitude limits you specify using the map projection limits.

```
latlim = [-80 80];
lonlim = [100 -120];
figure
axesm('robinson','MapLatLimit',latlim,'MapLonLimit',lonlim,...
    'Frame','on','Grid','on','MeridianLabel','on','ParallelLabel','on')
axis off
setm(gca,'MLabelLocation',60)
load coastlines
plotm(coastlat,coastlon)
```




Check that the axesm function set the origin and frame limits based on the values you specified using the MapLatLim and MapLonLim properties. The longitude of the origin should be located halfway between the longitude limits of 100 E and 120 W. Since the map spans 140 degrees, adding half of 140 to the western limit, the origin longitude should be 170 degrees. The frame is centered on this longitude with a half-width of 70 degrees and the origin latitude is on the Equator.

```
origin = getm(gca,'Origin')
origin = 1 \times 3
     0
          170
                    0
flatlim = getm(gca,'FLatLimit')
flatlim = 1 \times 2
   -80
           80
flonlim = getm(gca, 'FLonLimit')
flonlim = 1 \times 2
   -70
           70
```


Shift the western longitude to 40 degrees E (rather than 100 degrees) to include a little more of Asia. Use the setm function to assign a new value to the MapLonLimit property. Note the asymmetric appearance of the map.

setm(gca,'MapLonLimit',[40 -120])



To correct the asymmetry, shift the western longitude again, this time specifying the origin. While the MapLatLimit and MapLonLimit properties are convenient, the values of the Origin, FLatLimit, and FLonLimit properties take precedence. You must specify the value of the origin to achieve the map you intended. The best way to do this is to specify an empty value for the Origin property and let the setm command calculate the value.

```
setm(gca, 'MapLonLimit', [40 -120], 'Origin', [])
```



Create Cylindrical Projection Using Map Limit Properties


This example shows how to create cylindrical projection using map limit properties.

Load the coastline data.

```
load coastlines
```

Construct a Mercator projection covering the full range of permissible latitudes with longitudes covering a full 360 degrees starting at 60 West.

```
figure('Color','w')
axesm('mercator','MapLatLimit',[-90 90],'MapLonLimit',[-60 300])
axis off;
framem on;
gridm on;
mlabel on;
plabel on;
setm(gca,'MLabelLocation',60)
geoshow(coastlat,coastlon,'DisplayType','polygon')
```



The previous call to <code>axesm</code> is equivalent to:

```
axesm('mercator','Origin',[0\ 120\ 0],'FlatLimit',[-90\ 90],'FLonLimit',[-180\ 180]);
```

You can verify this by checking the properties.

Note that the map and frame limits are clamped to the range of $[-86\ 86]$ imposed by the read-only TrimLat property.

```
getm(gca,'MapLatLimit')
ans = 1×2
    -86    86

getm(gca,'FLatLimit')
ans = 1×2
    -86    86

getm(gca,'TrimLat')
ans = 1×2
    -86    86
```


Create Conic Projection Using Map Limit Properties

This example shows how to create a map of the standard version of the Lambert Conformal Conic projection covering latitudes 20 North to 75 North and longitudes covering 90 degrees starting at 30 degrees West.

```
Load coastline data and display it. The call to axesm above is equivalent to:

axesm('lambertstd','Origin', [0 15 0], 'FLatLimit',[20 75],FLonLimit',[-45 45])

load coastlines
figure('Color','w')
axesm('lambertstd','MapLatLimit',[20 75],'MapLonLimit',[-30 60])
axis off;
framem on;
gridm on;
mlabel on;
plabel on;
geoshow(coastlat, coastlon, 'DisplayType', 'polygon')
```




Create Southern Hemisphere Conic Projection

This example shows how to create a map of the standard version of the Lambert Conformal Conic projection into the Southern Hemisphere. The example overrides the default standard parallels and sets the MapLatLimit and MapLonLimit properties.

Load the coastline data MAT file, coastlines.mat.

load coastlines

Display the map, setting the MapLatLimit and MapLonLimit properties.



Create North-Polar Azimuthal Projection


This example shows how to construct a North-polar Equal-Area Azimuthal projection map extending from the Equator to the pole and centered by default on longitude 0.

Load coastline data set MAT file, coastlines.mat.

```
load coastlines


Create map. The call to axesm is equivalent to:
axesm('eqaazim','MLabelParallel',0,'Origin',[90 0 0],'FLatLimit',[-Inf 90]);

figure('Color','w')
axesm('eqaazim','MapLatLimit',[0 90])
axis off
framem on
gridm on
mlabel on
plabel on;
setm(gca,'MLabelParallel',0)
```



Plot the coast lines.

geoshow(coastlat,coastlon,'DisplayType','polygon')




Create South-Polar Azimuthal Projection

This example shows how to create a South-polar Stereographic Azimuthal projection map extending from the South Pole to 20 degrees S, centered on longitude 150 degrees West. Include a value for the Origin property in order to control the central meridian.

Load coastline data and display map.

```
load coastlines
figure('Color','w')
axesm('stereo','Origin',[-90 -150],'MapLatLimit',[-90 -20])
axis off;
framem on;
gridm on;
mlabel on;
plabel on;
setm(gca,'MLabelParallel',-20)
geoshow(coastlat,coastlon,'DisplayType','polygon')
```



The call to the axesm function above is equivalent to:


```
axesm('stereo','Origin',[-90 -150 0],'FLatLimit',[-Inf 70])
```

Create Equatorial Azimuthal Projection

This example shows how to create a map of an Equidistant Azimuthal projection with the origin on the Equator, covering from 10° E to 170° E. The origin longitude falls at the center of this range (90 E), and the map reaches north and south to within 10° of each pole.

Read coast data and display. The call to axesm is equivalent to axesm('eqaazim','Origin',[0 90 0],'FLatLimit',[-Inf 80]).

```
load coastlines
figure('Color','w')
axesm('eqdazim','FLatLimit',[],'MapLonLimit',[10 170])
axis off;
framem on;
gridm on;
mlabel on;
plabel on;
setm(gca,'MLabelParallel',0,'PLabelMeridian',60)
geoshow(coastlat,coastlon,'DisplayType','polygon')
```




Create General Azimuthal Projection

This example shows how to construct an Orthographic projection map with the origin centered near Paris, France. You can't use MapLatLimit or MapLonLimit here.

Read in coast data and display.

```
load coastlines
originLat = dm2degrees([48 48]);
originLon = dm2degrees([ 2 20]);
figure('Color','w')
axesm('ortho','Origin',[originLat originLon])
axis off; framem on; gridm on; mlabel on; plabel on;
setm(gca, 'MLabelParallel', 30, 'PLabelMeridian', -30)
geoshow(coastlat,coastlon,'DisplayType','polygon')
```



Create Long Narrow Oblique Mercator Projection

This example shows how to create a map with a long, narrow, oblique Mercator projection. The example shows the area 10 degrees to either side of the great-circle flight path from Tokyo to New York. You can't use MapLatLimit or MapLonLimit.

```
load coastlines
latTokyo = dm2degrees([ 35 40]);
lonTokyo = dm2degrees([139 45]);

latNewYork = dm2degrees([ 40 47]);
lonNewYork = dm2degrees([-73 58]);

[dist,az] = distance(latTokyo,lonTokyo,latNewYork,lonNewYork);
[midLat,midLon] = reckon(latTokyo,lonTokyo,dist/2,az);
midAz = azimuth(midLat,midLon,latNewYork,lonNewYork);

buf = [-10 10];

figure('Color','w')
axesm('mercator','Origin',[midLat midLon 90-midAz], ...
    'FLatLimit',buf,'FLonLimit',[-dist/2 dist/2] + buf)
axis off; framem on; gridm on; tightmap
geoshow(coastlat,coastlon,'DisplayType','polygon')
plotm([latTokyo latNewYork],[lonTokyo lonNewYork],'r-')
```



See Also

More About

- "The Map Frame" on page 4-41
- "Map and Frame Limits" on page 4-43

Switch Between Projections

Once you create an axesm-based map, whether map data is displayed or not, it is possible to change the current projection as well as many of its parameters. Use setm to reset the projection. The rest of this section describes the considerations and parameters involved in switching projections in an axesm-based map. Additional details are given for doing this with the geoshow function in "Change Map Projections Using geoshow" on page 4-37.


When you switch from one projection to another, setm clears out settings that were specific to the earlier projection, updates the map frame and graticule, and generally keeps the map covering the same part of the world—even when switching between azimuthal and non-azimuthal projections. But in some cases, you might need to further adjust the axesm-based map properties to achieve proper appearance. Settings that are suitable for one projection might not be appropriate for another. Most often, you'll need to update the positioning of your meridian and parallel labels.


Change Projection Updating Meridian and Parallel Labels

This example shows how to change the projection of an <code>axesm</code>-based map and update the meridian and parallel labels.

Create a Mercator projection with meridian and parallel labels.

```
axesm mercator
framem on; gridm on; mlabel on; plabel on
setm(gca,'LabelFormat','signed')
axis off
```






Get the default map and frame latitude limits for the Mercator projection. Note that both the frame and map latitude limits are set to 86 degrees north and south for the Mercator projection to maintain a safe distance from the singularity at the poles.

```
[getm(gca,'MapLatLimit'); getm(gca,'FLatLimit')]
ans = 2×2
   -86    86
   -86    86
```


Switch the projection to an orthographic azimuthal.

```
setm(gca,'MapProjection','ortho')
```



Specify new locations for the meridian and parallel labels.

```
setm(gca,'MLabelParallel',0,'PLabelMeridian',-90, ...
'PLabelMeridian',-30)
```




Change Projection Resetting Frame Limits

This example shows how to switch from one projection to another in an axesm-based map and reset the origin and frame limits, especially when mapping a small portion of the Earth.

Create an axesm-based map for a region of the United States in the Lambert Conformal Conic projection (the default projection for the usamap function).

```
latlim = [32 42];
lonlim = [-125 -111];
h = usamap(latlim, lonlim);
```




Read the usastatehi shapefile and return a subset of the shapefile contents, as defined by the latitude and longitude limits. The shaperead function returns the data in a structure called states .

```
states = shaperead('usastatehi.shp', 'UseGeoCoords', true, ...
   'BoundingBox', [lonlim', latlim']);
```

Save the latitude and longitude data from the structure in the vectors lat and lon .

```
lat = [states.Lat];
lon = [states.Lon];
Project patch objects on the map.
patchm(lat, lon, [0.5 0.5 1])
```



Change the projection to Lambert Equal Area Azimuthal and reset the origin and frame limits.

```
setm(gca,'MapProjection','eqaazim','Origin',[37 -118], ...
    'FLatLimit',[-Inf 6])
setm(gca,'mlinelocation',2,'plinelocation',2)
tightmap
```



Reprojection of Graphics Objects

Many Mapping Toolbox cartographic functions project features on an axesm-based map based on their designated latitude-longitude positions. The latitudes and longitudes are mathematically transformed to x and y positions using the formulas for the current map projection. If the map projection or its parameters change, objects on an axesm-based map can be automatically reprojected to update the map display accordingly.

The table summarizes the four common use cases for changing a map projection in an axesm-based map with setm or for reprojecting map data plotted on a regular MATLAB axes.

Mapping Use Case	Type of Axes	Reprojection Behavior
Plot geographic (latitude-longitude) vector coordinate data or data grid using a Mapping Toolbox function from releases prior to Version 2 (e.g., plotm)	axesm-based map	Automatic reprojection
Plot geographic vector data with geoshow	axesm-based map	No automatic reprojection; delete graphics objects prior to changing the projection and redraw them afterwards.
Plot data grids, images, and contours with geographic coordinates with geoshow	axesm-based map	Automatic reprojection; this behavior could change in a future release
Plot projected (x-y) vector or raster map data with mapshow or with a MATLAB graphics function (e.g., line, contour, or surf)	Regular axes	Manual reprojection (reproject coordinates with projinv/projfwd); delete graphics objects prior to changing the projection and redraw them afterwards.

You can use handlem to help identify which objects to delete when manual deletion is necessary. See "Work with Objects by Name" on page 4-96 for an example of its use.

Auto-Reprojection of Mapped Objects and Its Limitations

Using the setm function, you can change the current map projection on the fly if the map display was created in a way that permits reprojection. Note that map displays can contain objects that cannot be reprojected, and may need to be explicitly deleted and redrawn. Automatic reprojection will take place when you use setm to modify the MapProjection property, or any other axesm-based map property from the following list:

- AngleUnits
- Aspect
- FalseEasting
- FalseNorthing
- FLatLimit
- FLonLimit
- Geoid
- MapLatLimit

- MapLonLimit
- MapParallels
- Origin
- ScaleFactor
- TrimLat
- TrimLon
- Zone

Auto-reprojection takes place for objects created with any of the following Mapping Toolbox functions:

- contourm
- contour3m
- fillm
- fill3m
- gridm
- linem
- meshm
- patchm
- plotm
- plot3m
- surfm
- surfacem
- textm

The above Mapping Toolbox functions are analogous to standard MATLAB graphics functions having the same name, less the trailing m. You can use both types of functions to plot data on an <code>axesm-based</code> map, as long as you are aware that the standard MATLAB graphics functions do not apply map projection transformations, and therefore require you to specify positions in map x-y space.

In general, objects created with <code>geoshow</code> or with a combination of calls to <code>projfwd</code> followed by ordinary MATLAB graphics functions, such as <code>line</code>, <code>patch</code>, or <code>surface</code>, are not automatically reprojected. You should delete such objects whenever you change one or more of the <code>axesm-based</code> map properties listed above, and then redisplay them.

If you have preprojected vector or raster map data or read such data from files, you can display it with mapshow or standard MATLAB graphics functions, such as plot or mesh. If its projection is known and is included in the Mapping Toolbox projection libraries, you can use its parameters to project geodata in geographic coordinates to display it in the same axes.

Reprojectability of Maps Generated Using geoshow

If you want to be able to change the projection of a map on the fly, you should not use <code>geoshow</code>. Some display functions, such as <code>patchm</code>, <code>fillm</code>, <code>displaym</code>, and <code>linem</code>, enable you to reproject vector map data, but <code>geoshow</code> does not. That is, when you change an <code>axesm-based</code> map projection, with <code>setm</code> for example, vector map symbology that was created with <code>geoshow</code> will not be

transformed. Gridded data rendered with geoshow (when DisplayType is surface, texturemap, or contour), however, can be reprojected.

For examples of reprojection behavior with vector data and raster data, see "Change Map Projections Using geoshow" on page 4-37.

Change Map Projections Using geoshow

You can display latitude-longitude vector and raster geodata using the geoshow function (use mapshow to display preprojected coordinates and grids). When you use geoshow to display maps on an axesm-based map, the data are projected according to the map projection assigned when axesm, worldmap, or usamap created the map (e.g., axesm('mapprojection', 'mercator')).


You can also use geoshow to display latitude-longitude data on a regular axes (created by the axes function, for example). When you do this, the latitude-longitude data are displayed using a pcarree, which linearly maps longitude to x and latitude to y.

Change Map Projection with Vector Data Using geoshow

This example shows how to change a map projection when displaying vector data using <code>geoshow</code>. If you need to change projections when displaying both raster and vector geodata, you can combine these techniques. Removing vector graphic objects does not affect raster data already displayed.


Display vector data using geoshow.

```
figure;
axesm miller
h = geoshow('landareas.shp');
```



Delete the original map and change the projection.


```
delete(h)
setm(gca,'mapprojection','ortho')
geoshow('landareas.shp')
```



Change Map Projection with Raster Data Using geoshow


Get geoid heights and a geographic postings reference object from the EGM96 geoid model. Then, display the data using a Mercator projection.

```
[N,R] = egm96geoid;
axesm mercator
geoshow(N,R,'DisplayType','surface')
```



Change the projection using the setm function.

setm(gca,'mapprojection','mollweid')




See Also

Related Examples

"Summary and Guide to Projections" on page 8-45

The Map Frame

The map frame of an axesm-based map is the outline of the limits of a map, often in the form of a box, the "edge of the world," so to speak. The frame is displayed if the axesm-based map property Frame is set to 'on'. This can be accomplished upon axesm-based map creation with axesm, or later with setm, or with the direct command framem on. The frame is geographically defined as a latitude-longitude quadrangle that is projected appropriately. For example, on a map of the world, the frame might extend from pole to pole and a full 360° range of longitude. In appearance, the frame would take on the characteristic shape of the projection. The examples below are full-world frames shown in four very different projections.



Full-World Map Frames

As a map object, each of the previously displayed frames is identical; however, the selection of a display projection has varied their appearance.

You can manipulate properties beyond the latitude and longitude limits of the frame. Frame properties are established upon axesm-based map object creation; you can modify them subsequently with the setm and the framem functions. The command framem alone is a toggle for the Frame property, which controls the visibility of the frame. You can also call framem with property names and values to alter the appearance of the frame:

```
framem('FlineWidth',4,'FEdgeColor','red')
```

The frame is actually a patch with a default face color set to 'none' and a default edge color of black. You can alter these axesm-based map properties by manipulating the FFaceColor and FEdgeColor properties. For example, the command

```
setm(gca, 'FFaceColor', 'cyan')
```

makes the background region of your display resemble water. Since the frame patch is always the lowest layer of a map display, other patches, perhaps representing land, will appear above the "water." If an object is subsequently plotted "below" the frame patch, the frame altitude can be recalculated to lie below this object with the command framem reset. The frame is replaced and not reprojected.

Set the line width of the edge, which is 2 points by default, using the FLineWidth property.

The primary advantage of displaying the map frame is that it can provide positional context for other displayed map objects. For example, when vector data of the coasts is displayed, the frame provides the "edge" of the world.

See the framem reference page for more details.

Map and Frame Limits

The map and frame limits are two related axesm-based map properties that limit the map display to a defined region. The map latitude and longitude limits define the extents of geodata to be displayed, while the frame limits control how the frame fits around the displayed data. Any object that extends outside the frame limits is automatically trimmed.

The frame limits are also specified differently from the map limits. The map limits are in absolute geographic coordinates referenced to an origin at the intersection of the prime meridian and the equator, while the frame limits are referenced to the rotated coordinate system defined by the origin of the axesm-based map.

For all nonazimuthal projections, frame limits are specified as quadrangles ([latmin latmax] and [longmin longmax]) in the frame coordinate system. In the case of azimuthal projections, the frames are circular and are described by a polar coordinate system. One of the frame latitude limits must be a negative infinity (-Inf) to indicate an azimuthal frame (think of this as the center of the circle), while the other limit determines the radius of the circular frame (rlatmax). The longitude limits of azimuthal frames are inconsequential, since a full circle is always displayed.

If you are uncertain about the correct format for a particular projection frame limit, you can reset the formats to the default values using empty matrices.


Note For nonazimuthal projections in the normal aspect, the map extent is limited by the minimum of the map limits and the frame limits; hence, the two limits will coincide after evaluation. Therefore, if you manually change one set of limits, you might want to clear the other set to get consistent limits.

The Map Grid

The *map grid* is the set of displayed meridians and parallels, also known as a *graticule*. Display the grid by setting the axesm-based map property Grid to 'on'. You can do this when you create axesm-based maps with axesm, with setm, or with the direct command gridm on.

Control Grid Spacing

To control display of meridians and parallels, set a scalar meridian spacing or a vector of desired meridians in the MLineLocation property. The property PLineLocation serves a corresponding purpose for parallels. The default values place grid lines every 30° for meridians and every 15° for parallels.



Layer Grids

By default, the grid is placed as the top layer of any display. You can alter this by changing the GAltitude property, so that other map objects can be placed "above" the grid. The new grid is drawn at its new altitude. The units used for GAltitude are specified with the daspectm function.

To reposition the grid back to the top of the display, use the command gridm reset. You can also control the appearance of grid lines with the GLineStyle and GLineWidth properties, which are ':' and 0.5, respectively, by default.


Limit Grid Lines

The Miller projection is an example in which all the meridians can extend to the poles without appearing to be cluttered. In other projections, such as the orthographic (below), the map grid can

obscure the surface where they converge. Two axesm-based map properties, MLineLimit and MLineException, enable you to control such clutter:


- Use the MLineLimit property to specify a pair of latitudes at which to terminate the meridians. For example, setting MLineLimit to [-75 75] completely clears the region above and below this latitude range of meridian lines.
- If you want some lines to reach the poles but not others, you can specify them with the MLineException property. For example, if MLineException is set to [-90 0 90 180], then the meridians corresponding to the four cardinal longitudes will continue past the limit on to the pole.

The use of these properties is illustrated in the figure below. Note that there are two corresponding axesm-based map properties, PLineLimit and PLineException, for controlling the extent of displayed parallels.




Default grid allows all displayed meridians to extend to the poles:

```
axesm('MapProjection','ortho',...
'Origin',[40,40,14],...
'Grid','on','Frame','on');
```



The property MLineLimit truncates meridians at given latitudes:

```
axesm('MapProjection','ortho',...
'Origin',[40,40,14],...
'Grid','on','Frame','on',...
'MLineLimit', [-75 75]);
```



The property MLineLineException permits certain meridians to extend to the poles, regardless of MLineLimit:

```
axesm('MapProjection','ortho',...
'Origin',[40,40,14],...
'Grid','on','Frame','on',...
'MLineLimit', [-75 75],...
'MLineException',[-90 0 90 180]);
```

Label Grids

You can label displayed parallels and meridians. MeridianLabel and ParallelLabel are on-off properties for displaying labels on the meridians and parallels, respectively. They are both 'off' by default. Initially, the label locations coincide with the default displayed grid lines, but you can alter this by using the PlabelLocation and MlabelLocation properties. These grid lines are labeled across the north edge of the map for meridians and along the west edge of the map for parallels. However, the property MlabelParallel allows you to specify 'north', 'south', 'equator', or a specific latitude at which to display the meridian labels, and PlabelMeridian allows the choice of 'west', 'east', 'prime', or a specific longitude for the parallel labels. By default, parallel labels are displayed in the range of 0° to 90° north and south of the equator while meridian labels are

displayed in the range of 0° to 180° east and west of the prime meridian. You can use the mlabelzero22pi function to redisplay the meridian labels in the range of 0° to 360° east of the prime meridian.

Properties affecting grid labeling are listed below.

Property	Effect	
MeridianLabel	Toggle display of meridian labels	
ParallelLabel	Toggle display of parallel labels	
MlabelLocation	Alternate interval for labeling meridians	
PlabelLocation	Alternate interval for labeling parallels	
MlabelParallel	Keyword or latitude for placing meridian labels	
PlabelMeridian	Keyword or longitude for placing parallel labels	
mlabelzero22pi(function)	Relabel meridians with positive angle from 0° to 360°	

For complete descriptions of all <code>axesm-based</code> map properties, refer to the axesm-Based Map Properties reference page.

Summary of Polygon Display Functions

The following table lists the available Mapping Toolbox patch and polygon display functions.

Function	Used For	
geoshow	Display map latitude and longitude data in 2-D on axesm-based maps	
mapshow	Display map data without projection in 2-D on axes	
patchm	Patch objects projected on axesm-based maps	
patchesm	Patches projected as individual objects on axesm-based maps	
fillm	Filled 2-D map patches on axesm-based maps	
fill3m	Filled 3-D map patches in 3-D space on axesm-based maps	
geoplot	Display point, line, and polygon data on geographic axes	

geoshow and mapshow

The geoshow and mapshow functions provide a superset of functionality for displaying geographic (latitude-longitude) and projected (xy) geospatial data, respectively, in two dimensions. These functions accept geospatial tables, geographic data structures (geostructs and mapstructs), and coordinate vector arrays, but can also directly read shapefiles and spatially referenced raster files. To control how MATLAB renders the data, create symbol specifications by using the makesymbolspec function.

patchm, patchesm, fillm, and fill3m

Mapping Toolbox provides two low-level patch drawing functions, patchm and patchesm. The patchm function creates one displayed object that can contain multiple unconnected faces. Unlike MATLAB patch display functions, which do not support unconnected patch faces, patchm separates unconnected faces using NaN values. Alternatively, the patchesm function treats each face as a separate object and returns an array of patch objects. In general, patchm requires more memory but is faster than patchesm. The patchesm function is useful if you need to manipulate the appearance of individual patches (as thematic maps often require).

The fillm and fill3m functions make use of the patchm function.

geoplot

The geoplot function displays point, line, and polygon data on geographic axes. This function accepts geospatial tables and shape objects in any supported projected or geographic coordinate reference system (CRS), and coordinate vectors in geographic coordinates. Unlike the other functions listed on this page, the geoplot function creates a Polygon object when you display polygon data.

See Also

Properties

Patch Properties | Polygon Properties

More About

"Create and Display Polygons" on page 2-8 $\,$

Display Vector Data as Points and Lines

This example shows how to display vector data on an axesm-based map using points and lines. axesm-based maps enable you to display geographic data using a map projection.

Load a MAT-file containing the coordinates of global coastlines into the workspace. The variables within the MAT-file, coastlat and coastlon, specify numeric latitude and longitude coordinates.

```
load coastlines
```

Set up a map using the Mollweide projection. Customize the color and line width of the frame.


```
figure
axesm mollweid
framem("FEdgeColor","b","FLineWidth",0.5)
```

Display the coastline data by using the plotm function. Customize the thickness and color of the line.

```
plotm(coastlat,coastlon,"LineWidth",1,"Color","b")
```

Specify the locations of three cities (Cairo, Rio de Janeiro, and Perth). Plot red star markers at those locations.


```
citylat = [30 -23 -32];
citylon = [32 -43 116];
plotm(citylat,citylon,"r*")
```



Find the coordinates of two tracks and display them on the map.

- Display a great circle track from Cairo to Rio de Janeiro using a dashed magenta line.
- Display a rhumb line track from Cairo to Perth using a solid black line.

```
[gclat,gclon] = track2("gc",citylat(1),citylon(1),citylat(2),citylon(2));
plotm(gclat,gclon,"m--")
[rhlat,rhlon] = track2("rh",citylat(1),citylon(1),citylat(3),citylon(3));
plotm(rhlat,rhlon,"k")
```




Alternatively, you can plot geographic data over axesm-based maps by using the geoshow function.

Tips

- To plot data that is already in projected coordinates, use a regular axes object and the mapshow function.
- You can create a similar plot by using geographic axes and the **geoplot** function. Geographic axes enable you to specify basemaps, change the geographic limits, and interactively pan and zoom. The **geoplot** function displays data into a Web Mercator map projection.

```
figure
geoplot(coastlat,coastlon,"b")
hold on
geoplot(citylat,citylon,"*r")
geoplot(gclat,gclon,"m--",rhlat,rhlon,"k")
```

geobasemap topographic
geolimits([-72 85],[-180 180])



See Also

Functions

axesm | plotm | geoshow | mapshow | geoplot

Properties

axesm-Based Map Properties

Related Examples

• "Display Vector Data as Lines and Patches" on page 4-52

Display Vector Data as Lines and Patches

This example shows how to display vector data on axesm-based maps using lines or patches (filled polygons). axesm-based maps enable you to display geographic data using a map projection.

Load data containing the latitude and longitude coordinates for these polygon and line shapes. The data separates individual polygons and lines using NaN values.

- uslat and uslon Three polygons representing the conterminous United States, Long Island, and Martha's Vineyard.
- gtlakelat and gtlakelon Three polygons representing the Great Lakes.
- statelat and statelon Lines representing the borders between states.

```
load conus
```

Use the coordinate data to create polygon and line shapes. Combine the shapes into a geospatial table.

Read a river network into a geospatial table containing line shapes. Clip the line shapes to a region that covers the conterminous United States.

```
riversGT = readgeotable("worldrivers.shp");
uslatlim = [min(uslat) max(uslat)];
uslonlim = [min(uslon) max(uslon)];
clipped = geoclip(riversGT.Shape,uslatlim,uslonlim);
riversGT.Shape = clipped;
```


Set up an axesm-based map to display the state coordinates, turning on the map frame, map grid, and the meridian and parallel labels. As conic projections are appropriate for mapping the entire United States, create a map using an Albers equal-area conic projection ("eqaconic"). Specifying map limits that contain the region of interest automatically centers the projection on an appropriate longitude. The frame encloses just the mapping area, not the entire globe. As a general rule, you should specify map limits that extend slightly outside your area of interest (worldmap and usamap do this for you). Conic projections need two standard parallels (latitudes at which scale distortion is zero). A good rule is to set the standard parallels at one-sixth of the way from both latitude extremes. Or, to use default latitudes for the standard parallels, simply provide an empty matrix in the call to axesm.

```
figure
axesm("MapProjection","eqaconic","MapParallels",[], ...
```

```
"MapLatLimit",uslatlim + [-2 2], ...
"MapLonLimit",uslonlim + [-2 2])
axis off
framem
gridm
mlabel
plabel
```


Display the area occupied by the conterminous United States as a patch. Note that the order in which add layers to a map can affect visibility because some layers can hide other layers. For example, because some US state boundaries follow major rivers, display the rivers last to avoid obscuring them.

```
geoshow(conusGT(1,:), "FaceColor",[1 0.5 0.3], "EdgeColor", "none")
```




Display the Great Lakes on top of the land area.

```
geoshow(conusGT(2,:), "FaceColor", "cyan", "EdgeColor", "none")
```




Display the line shapes containing state boundaries.

geoshow(conusGT(3,:),"Color","k")



Display the river network.


geoshow(riversGT,"Color","blue")



Tips

- To plot data that is already in projected coordinates, use a regular axes object and the mapshow function.
- Starting in R2022a, you can create a similar plot by using geographic axes and the geoplot function. Geographic axes enable you to specify basemaps, change the geographic limits, and interactively pan and zoom. The geoplot function accepts shapes with coordinates in any supported projected or geographic coordinate reference system (CRS) and displays the data into a Web Mercator map projection.

```
figure
geoplot(conusGT(1,:), "FaceColor", [1 0.5 0.3], "EdgeColor", "none")
hold on
geoplot(conusGT(2,:), "FaceColor", "cyan", "EdgeColor", "none")
geoplot(conusGT(3,:), "k")
geoplot(riversGT, "Color", "blue")
alpha(1)
geobasemap topographic
```



See Also

Functions

axesm | geoclip | geoshow | mapshow | geoplot

Properties

axesm-Based Map Properties

More About

- "Create and Display Polygons" on page 2-8
- "Display Vector Data as Points and Lines" on page 4-49

Types of Data Grids and Raster Display Functions

Mapping Toolbox functions and GUIs display both regular and geolocated data grids originating in a variety of formats. Recall that regular data grids require a *referencing vector or matrix* that describes the sampling and location of the data points, while geolocated data grids require matrices of latitude and longitude coordinates.

The data grid display functions are geographic analogies to the MATLAB surface drawing functions, but operate specifically on <code>axesm</code>-based maps. Like the line-plotting functions discussed in the previous chapter, some Mapping Toolbox grid function names correspond to their MATLAB counterparts with an <code>m</code> appended.

Note Mapping Toolbox functions beginning with mesh are used for regular data grids, while those beginning with surf are reserved for geolocated data grids. This usage differs from the MATLAB definition; mesh plots are used for colored wire-frame views of the surface, while surf displays colored faceted surfaces.

Surface map objects can be displayed in a variety of different ways. You can assign colors from the figure colormap to surfaces according to the values of their data. You can also display images where the matrix data consists of indices into a colormap or display the matrix as a three-dimensional surface, with the z-coordinates given by the map matrix. You can use monochrome surfaces that reflect a pseudo-light source, thereby producing a three-dimensional, shaded relief model of the surface. Finally, you can use a combination of color and light shading to create a lighted shaded relief map.

The following table lists the available Mapping Toolbox surface map display functions.

Function	Used For	
geoshow	Display map latitude and longitude data in 2-D	
mapshow	Display map data without projection in 2-D	
meshm	Project regular data grid on axesm-based map	
surfm	Project geolocated data grid on axesm-based map	
pcolorm	Project regular data grid in $z = 0$ plane on axesm-based map	
surfacem	Project and add geolocated data grid to axesm-based map	
surflm	3-D shaded surface with lighting on axesm-based map	
meshlsrm	3-D lighted shaded relief of regular data grid on axesm-based map	
surflsrm	3-D lighted shaded relief of geolocated data grid on axesm-based map	

Fit Gridded Data to the Graticule

The toolbox projects surface objects in a manner similar to the traditional methods of map making. A cartographer first lays out a grid of meridians and parallels called the *graticule*. Each graticule cell is a geographic quadrangle. The cartographer calculates or interpolates the appropriate x-y locations for every vertex in the graticule grid and draws the projected graticule by connecting the dots. Finally, the cartographer draws the map data freehand, attempting to account for the shape of the graticule cells, which usually change shape across the map. Similarly, the toolbox calculates the x-y locations of the four vertices of each graticule cell and warps or samples the matrix data to fit the resulting quadrilateral.

In mapping data grids using the toolbox, as in traditional cartography, the finer the mesh (analogous to using a graticule with more meridians and parallels), the greater precision the projected map display will have, at the cost of greater effort and time. The graticule in a printed map is analogous to the spacing of grid elements in a regular data grid, the Mapping Toolbox representation of which is two-element vectors of the form [number-of-parallels, number-of-meridians]. The graticule for geolocated data grids is similar; it is the size of the latitude and longitude coordinate matrices: number-of-parallels = mrows-1 and number-of-meridians = ncols-1. However, because geolocated data grids have arbitrary cell corner locations, spacing can vary and thus their graticule is not a regular mesh.

Fit Gridded Data to Fine and Coarse Graticules

This example shows how to fit gridded data to fine and coarse graticules. The choice of graticule is a balance of speed over precision in terms of positioning the grid on the map. Typically, there is no point to specifying a mesh finer than the data resolution (in this example, 180-by-360 grid cells). In practice, it makes sense to use coarse graticules for development tasks and fine graticules for final graphics production.


Note that, regardless of the graticule resolution, the grid data is unchanged. In this case, the data grid is a 180-by-360 matrix, and regardless of where it is positioned, the data values are unchanged.

Load elevation raster data and a geographic cells reference object.

```
load topo60c
```


Set up a Robinson projection, specify a coarse (10-by-20) cell graticule, and display the data mapped to the graticule using a colormap appropriate for elevation data. Notice that for this coarse graticule, the edges of the map do not appear as smooth curves.

```
figure
axesm robinson
spacing = [10 20];
m = meshm(topo60c,topo60cR,spacing);
demcmap(topo60c)
```




Now reset the graticule, using the \mathtt{setm} function, to make it less coarse, [50 100]. Notice that the jagged edges effect is now negligible.

setm(m,'MeshGrat',[50 100])



Reset the graticule again, this time to a very fine grid using the setm function. Notice that the result does not appear to be any better than the original display with the default [50 100] graticule, but it took much longer to produce. Making the mesh more precise is a trade-off of resolution versus time and memory usage.

setm(m, 'MeshGrat', [200 400])



Create 3-D Displays with Raster Data

This example shows how to create a 3-D display of raster data on an axesm-based map by setting up surface views, which requires explicit horizontal coordinates. The simplest way to display raster data is to assign colors to matrix elements according to their data values and view them in two dimensions. Raster data maps also can be displayed as 3-D surfaces using the matrix values as the z data. The difference between regular raster data and a geolocated data grid is that each grid intersection for a geolocated grid is explicitly defined with x-y or latitude/longitude matrices or is interpolated from a graticule, while a regular matrix only implies these locations (which is why it needs a reference object).

Display Elevation Data in 3-D

Load elevation data and a geographic cells reference object for the Korean peninsula. Transform the data and reference object to a fully geolocated data grid using the geographicGrid function.

```
load korea5c
[lat,lon] = geographicGrid(korea5cR);
```

Next use the km2deg function to convert the units of elevation from meters to degrees, so they are commensurate with the latitude and longitude coordinate matrices.

```
korea5c = km2deg(korea5c/1000);
```

Observe the results by typing the whos command. The lat and lon coordinate matrices form a mesh the same size as korea5c. This is a requirement for constructing 3-D surfaces. In lon, all columns contain the same number for a given row, and in lat, all rows contain the same number for a given column.


whos

Name	Size	Bytes	Class
description	2x64	256	char
korea5c	180x240	345600	double
korea5cR	1x1	128	<pre>map.rasterref.GeographicCellsReference</pre>
lat	180×240	345600	double
lon	180×240	345600	double
source	2x76	304	char

Now set up an axesm-based map with the equal area conic projection and, instead of using the meshm function to make this map, display the geolocated data grid using the surfm function. Set an appropriate colormap. This produces a map that is really a 3-D view seen from directly overhead (the default perspective). To appreciate that, all you need to do is to change your viewpoint.


```
axesm('MapProjection','eqaconic','MapParallels',[],...
    'MapLatLimit',[30 45],'MapLonLimit',[115 135])
surfm(lat,lon,korea5c,korea5c)
demcmap(korea5c)
tightmap
```

Attribut



Specify a viewing azimuth of 60 degrees (from the east southeast) and a viewing elevation of 30 degrees above the horizon, using the view function.

view(60,30)



See Also

Functions

geographicGrid|surfm|axesm

ObjectsGeographicCellsReference

Create Map Displays with Geographic Data

There are many geospatial data sets that contain data with coordinates in latitude and longitude in units of degrees. This example illustrates how to import geographic data with coordinates in latitude and longitude, display geographic data in a map display, and customize the display.

In particular, this example illustrates how to

- Import specific geographic vector and raster data sets
- Create map displays and visualize the data
- Display multiple data sets in a single map display
- · Customize a map display with a scale ruler and north arrow
- Customize a map display with an inset map

Example 1: Import Polygon Geographic Vector Data

Geographic vector data can be stored in a variety of different formats, for example shapefile and GPS Exchange (GPX) formats. This example imports polygon geographic vector data from a shapefile. Vertices in a shapefile can be either in geographic coordinates (latitude and longitude) or in a projected coordinate reference system.


Read USA state boundaries from the usastatehi.shp file included with the Mapping Toolbox $^{\text{m}}$ software. The state boundaries are in latitude and longitude.

```
states = shaperead('usastatehi.shp','UseGeoCoords',true);
```

Example 2: Display Polygon Geographic Vector Data

Display the polygon geographic vector data onto an axesm-based map (previously referred to as map axes). Since the geographic extent is in the United States, you can use usamap to set up the map. Use geoshow to project and display the geographic data onto the map. Display an ocean color in the background by setting the frame's face color.

```
figure
ax = usamap('conus');
oceanColor = [0.3010 0.7450 0.9330];
landColor = [0.9290 0.6940 0.1250];
setm(ax,'FFaceColor',oceanColor)
geoshow(states,'FaceColor',landColor)
title({'Conterminous USA State Boundaries', ...
    'Polygon Geographic Vector Data'})
```



Example 3: Import Point and Line Geographic Vector Data

Import point geographic vector data from the boston_placenames.gpx file included with the Mapping Toolbox $^{\text{TM}}$ software. The file contains latitude and longitude coordinates of geographic point features in part of Boston, Massachusetts, USA. Use the readgeotable function to read the GPX file and return a geospatial table with one row for each point and its attributes.

```
placenames = readgeotable('boston_placenames.gpx');
```

Import line vector data from the $sample_route.gpx$ file included with the Mapping Toolbox m software. The file contains latitude and longitude coordinates for a GPS route from Boston Logan International Airport to The MathWorks, Inc in Natick Massachusetts, USA. Use the readgeotable function to read the GPX file and return a geospatial table contains each point along the route.

```
route = readgeotable('sample_route.gpx');
```

Example 4: Display Point and Line Geographic Vector Data


Display the geographic vector data in an axesm-based map centered around the state of Massachusetts, using the data from the state boundaries and the GPX files. The coordinates for all of these data sets are in latitude and longitude.

Find the state boundary for Massachusetts.

```
stateName = 'Massachusetts';
ma = states(strcmp({states.Name}, stateName));
```

Use usamap to setup a map for the region surrounding Massachusetts. Color the ocean by setting the frame's face color. Display the state boundaries and highlight Massachusetts by using geoshow to display the geographic data onto the map. Since the GPX route is a set of points stored in a geopointshape vector, supply the latitude and longitude coordinates to geoshow to display the route as a line.

```
figure
ax = usamap('ma');
maColor = [0.4660 0.6740 0.1880];
setm(ax,'FFaceColor',oceanColor)
geoshow(states,'FaceColor',landColor)
geoshow(ma,'FaceColor',maColor)
geoshow(placenames);
geoshow(route.Shape.Latitude,route.Shape.Longitude);
title({'Massachusetts and Surrounding Region','Placenames and Route'})
```




Example 5: Set Latitude and Longitude Limits Based on Data Extent

Zoom into the map by computing new latitude and longitude limits for the map using the extent of the placenames and route data. Extend the limits by 0.05 degrees.

```
lat = [route.Shape.Latitude; placenames.Shape.Latitude];
lon = [route.Shape.Longitude; placenames.Shape.Longitude];
[latlim,lonlim] = geoquadpt(lat,lon);
[latlim,lonlim] = bufqeoquad(latlim,lonlim,0.05,0.05);
```

Construct an axesm-based map with the new limits and display the geographic data.

```
figure
ax = usamap(latlim,lonlim);
setm(ax,'FFaceColor',oceanColor)
geoshow(ma,'FaceColor',maColor)
geoshow(placenames)
geoshow(route.Shape.Latitude,route.Shape.Longitude)
title('Closeup of Placenames and Route')
```



Example 6: Import Geographic Raster Data

Geographic raster data can be stored in a variety of different formats, for example GeoTIFF, Esri Grid, DTED, and ENVI formats. To read data in these formats, use the readgeoraster function.

To read an image associated with a worldfile, use the imread and worldfileread functions instead. Use imread to read the image and worldfileread to read the worldfile and construct a spatial referencing object. For this example, import data for the region surrounding Boston, Massachusetts. The coordinates of the image are in latitude and longitude.


```
filename = 'boston_ovr.jpg';
RGB = imread(filename);
R = worldfileread(getworldfilename(filename), 'geographic', size(RGB));
```

Example 7: Display Geographic Raster Data

Display the RGB image onto an axesm-based map. The limits of the map are set to the limits defined by the spatial referencing object, R. The coordinates of the data are in latitude and longitude.

```
figure
ax = usamap(RGB,R);
setm(ax,'MLabelLocation',0.05,'PLabelLocation',0.05, ...
    'MLabelRound', -2, 'PLabelRound', -2)
geoshow(RGB,R)
title('Boston Overview')
```


Boston Overview



Example 8: Display Geographic Vector and Raster Data

You can display raster and vector data in a single map display. Since the coordinates for all of these data sets are in latitude and longitude, use geoshow to display them in a single map display. Setup new limits based on the limits of the route, placenames, and the overview image.

```
lat = [route.Shape.Latitude' placenames.Shape.Latitude' R.LatitudeLimits];
lon = [route.Shape.Longitude' placenames.Shape.Longitude' R.LongitudeLimits];
[latlim,lonlim] = geoquadpt(lat,lon);
figure
ax = usamap(latlim,lonlim);
setm(ax, 'GColor', 'k', 'PLabelLocation', 0.05, 'PLineLocation', 0.05)
geoshow(RGB,R)
geoshow(ma.Lat,ma.Lon,'LineWidth',2,'Color','y')
geoshow(placenames)
geoshow(route.Shape.Latitude,route.Shape.Longitude)
title('Boston Overview and Geographic Vector Data')
```



Example 9: Customize a Map Display with a Scale Ruler


Customize a map display by including a scale ruler. A scale ruler is a graphic object that shows distances on the ground at the correct size for the projection. This example illustrates how to construct a scale ruler that displays horizontal distances in international miles.

Compute latitude and longitude limits of Massachusetts and extend the limits by 0.05 degrees by using the bufgeoquad function.

```
[latlim,lonlim] = geoquadline(ma.Lat,ma.Lon);
[latlim,lonlim] = bufqeoquad(latlim,lonlim,0.05,0.05);
```

Display the state boundary, placenames, route, and overview image onto the map.

```
figure
ax = usamap(latlim,lonlim);
setm(ax,'FFaceColor',oceanColor)
geoshow(states,'FaceColor',landColor)
geoshow(ma,'LineWidth',1.5,'FaceColor',maColor)
geoshow(RGB,R)
geoshow(placenames)
geoshow(route.Shape.Latitude,route.Shape.Longitude)
titleText = 'Massachusetts and Surrounding Region';
title(titleText)
```




Insert a scale ruler. You can determine a location for the scale ruler by using the ginput function as shown below:

```
[xLoc,yLoc] = ginput(1);
```

A location previously chosen is set below.

```
xLoc = -127800;
yLoc = 5014700;
```




Example 10: Customize a Map Display with a North Arrow

Customize the map by adding a north arrow. A north arrow is a graphic element pointing to the geographic North Pole.

Use latitude and longitude values to position the north arrow.

```
northArrowLat = 42.5;
northArrowLon = -70.25;
northarrow('Latitude',northArrowLat,'Longitude',northArrowLon);
title({titleText,'with Scale Ruler and North Arrow'})
```




73.5°W 73.0°W 72.5°W 72.0°W 71.5°W 71.0°W 70.5°W 70.0°W

Example 11: Customize a Map Display with an Inset Map

Customize the map by adding an inset map. An inset map is a small map within a larger map that enables you to visualize the larger geographic region of your main map. Create a map for the surrounding region as an inset map. Use the axes function to contain and position the inset map. In the inset map:

- Display the state boundaries for the surrounding region
- Plot a red box to show the extent of the main map



Data Set Information

The file boston_placenames.gpx is from the Bureau of Geographic Information (MassGIS), Commonwealth of Massachusetts, Executive Office of Technology and Security Services. For more information about the data sets, use the command type boston_placenames_gpx.txt.

The file boston_ovr.jpg includes materials copyrighted by GeoEye, all rights reserved. GeoEye was merged into the DigitalGlobe corporation on January 29th, 2013. For more information about the data set, use the command type boston ovr.txt.

See Also

usamap | geoshow | scaleruler | northarrow | geoplot | geoscatter

Create Maps with Data in Projected Coordinate Reference Systems

This example illustrates how to import and display geographic data that contain coordinates in a projected coordinate reference system.

In particular, this example illustrates how to

- Import specific raster and vector data sets
- Create map displays for visualizing the data
- Display multiple data sets in a map display
- Display multiple data sets with coordinates in geographic and projected coordinate reference systems in a single map display

Example 1: Import Raster Data in Projected Coordinate Reference System

Geographic raster data that contains coordinates in a projected coordinate reference system can be stored in a variety of different formats, including standard file formats such as GeoTIFF, Spatial Data Transfer Standard (SDTS), NetCDF, HDF4, or HDF5. This example illustrates importing data from a GeoTIFF file. The data in the file contains coordinates in the projected map coordinate reference system *Massachusetts State Plane Mainland Zone coordinate system*.

The coordinates of the image in the GeoTIFF file, boston.tif, are in a projected coordinate reference system. You can determine that by using the geotiffinfo function and examine the PCS and Projection field values.

```
info = geotiffinfo('boston.tif');
disp(info.PCS)

NAD83 / Massachusetts Mainland

disp(info.Projection)

SPCS83 Massachusetts Mainland zone (meters)
```

The length unit of the coordinates are defined by the UOMLength field in the info structure.

```
disp(info.UOMLength)
US survey foot
```


To import the image and the spatial referencing object, use readgeoraster.

```
[boston,R] = readgeoraster('boston.tif');
```

Example 2: Display Raster Data in Projected Coordinate Reference System

You can display the image on a regular MATLAB axes using mapshow, which displays the image and sets the axes limits to the limits defined by the referencing object, R. The coordinates, as mentioned above, are in US survey foot and are relative to an origin to the southwest of the map, which is why the numbers are large. The coordinates are always positive within the zone.

```
mapshow(boston,R)
axis image
title('Boston')
```



Example 3: Import Vector Data in Projected Coordinate Reference System

Geographic vector data that contains coordinates in a projected coordinate reference system can be stored in shapefiles. This example illustrates how to import vector data in a projected coordinate reference system from the shapefile, boston roads.shp.

Import vector line data from the boston roads.shp file as a geospatial table.

```
roads = readgeotable('boston roads.shp');
```

The Shape variable of the table contains information about the line shapes. Query the projected coordinate reference system of the shapes.

```
roads.Shape.ProjectedCRS
```

Example 4: Display Vector and Raster Data in Projected Coordinate Reference System


The vector and raster data in this example are in the same projected coordinate reference system. However, the vector data is in length units of meter, while the raster data is in length unit of survey foot. Convert the raster data to length units of meter and display the data on the same axes.

Convert the coordinates of the raster image from units of US survey foot to meter.

```
R.XWorldLimits = R.XWorldLimits * unitsratio('m','sf');
R.YWorldLimits = R.YWorldLimits * unitsratio('m','sf');
```

Display the raster image and vector data using mapshow.

```
figure
mapshow(boston,R)
mapshow(roads)
title('Boston and Roads')
```



Example 5: Display Data in both Geographic and Projected Coordinate Reference Systems

You may have geographic data whose coordinates are in latitude and longitude and other data whose coordinates are in a projected coordinate reference system. You can display these data sets in the same map display. This example illustrates how to display data in a geographic coordinate reference system (latitude and longitude) with data in a projected map coordinate reference system (Massachusetts State Plane Mainland Zone coordinate system).

Read a raster image with a worldfile whose coordinates are in latitude and longitude. Use imread to read the image and worldfileread to read the worldfile and construct a spatial referencing object.

```
filename = 'boston_ovr.jpg';
overview = imread(filename);
overviewR = worldfileread(getworldfilename(filename), 'geographic', size(overview));
```

To display the overview image and the GeoTIFF image in the same map display, you need to create a map display using a Mapping Toolbox™ projection structure containing the projection information for the data in the projected coordinate reference system, *Massachusetts State Plane Mainland Zone coordinate system*. To make a map display in this system, you can use the projection information contained in the GeoTIFF file. Use the geotiff2mstruct function to construct a Mapping Toolbox™ projection structure, from the contents of the GeoTIFF information structure. The geotiff2mstruct function returns a projection in units of meters. Use the projection structure to define the projection parameters for the map display.

```
mstruct = geotiff2mstruct(info);
```

Use the latitude and longitude limits of the Boston overview image.


```
latlim = overviewR.LatitudeLimits;
lonlim = overviewR.LongitudeLimits;
```

Create an axesm-based map by using the projection information stored in the map projection structure and set the map latitude and longitude limits. Display the geographic data in the map. geoshow projects the latitude and longitude coordinates.

figure

```
ax = axesm(mstruct, 'Grid', 'on',...
    'GColor', [.9 .9 .9], ...
    'MapLatlimit', latlim, 'MapLonLimit', lonlim, ...
    'ParallelLabel', 'on', 'PLabelLocation', .025, 'PlabelMeridian', 'west', ...
    'MeridianLabel', 'on', 'MlabelLocation', .05, 'MLabelParallel', 'south', ...
    'MLabelRound', -2, 'PLabelRound', -2, ...
    'PLineVisible', 'on', 'PLineLocation', .025, ...
    'MLineVisible', 'on', 'MlineLocation', .05);
geoshow(overview, overviewR)
axis off
tightmap
title({'Boston and Surrounding Region', 'Geographic Coordinates'})
```


Boston and Surrounding Region Geographic Coordinates



Since the coordinates of the GeoTIFF image are in a projected coordinate reference system, use mapshow to overlay the more detailed Boston image onto the display. Plot the boundaries of the Boston image in red.


```
mapshow(boston, R)
plot(R.XWorldLimits([1 1 2 2 1]), R.YWorldLimits([1 2 2 1 1]), 'Color', 'red')
title({'Boston and Surrounding Region', 'Geographic and Projected Coordinates'})
```

Boston and Surrounding Region Geographic and Projected Coordinates



Zoom to the geographic region of the GeoTIFF image by setting the axes limits to the limits of the Boston image and add a small buffer. Note that the buffer size (delta) is expressed in meters.

```
delta = 1000;
xLimits = R.XWorldLimits + [-delta delta];
yLimits = R.YWorldLimits + [-delta delta];
xlim(ax,xLimits)
ylim(ax,yLimits)
setm(ax, 'Grid', 'off');
```



Boston and Surrounding Region Geographic and Projected Coordinates

You can overlay the road vectors onto the map display. Use a symbol specification to give each class of road its own color.

```
roadColors = makesymbolspec('Line',...
title({'Boston and Surrounding Region', 'Including Boston Roads'})
```


Boston and Surrounding Region Including Boston Roads

You can also overlay data from a GPS stored in a GPX file. Import point geographic vector data from the boston_placenames.gpx file included with the Mapping Toolbox $^{\text{\tiny M}}$ software. The file contains latitude and longitude coordinates of geographic point features in part of Boston, Massachusetts, USA.

```
placenames = readgeotable('boston_placenames.gpx');
```

Overlay the placenames onto the map and increase the marker size, change the markers to circles and set their edge and face colors to yellow.

```
geoshow(placenames, 'Marker','o', 'MarkerSize', 6, ...
    'MarkerEdgeColor', 'y', 'MarkerFaceColor','y')
title({'Boston and Surrounding Region','Including Boston Roads and Placenames'})
```



Boston and Surrounding Region Including Boston Roads and Placenames

Data Set Information

The files boston.tif and boston_ovr.jpg include materials copyrighted by GeoEye, all rights reserved. GeoEye was merged into the DigitalGlobe corporation on January 29th, 2013. For more information about the data sets, use the commands type boston.txt and type boston_ovr.txt.

The files boston roads.shp and boston placenames.gpx are from the Bureau of Geographic Information (MassGIS), Commonwealth of Massachusetts, Executive Office of Technology and Security Services. For more information about the data sets, use the commands type boston roads.txt and type boston placenames gpx.txt.

Pick Locations Interactively


You can use Mapping Toolbox functions to interact with axesm-based maps. This section describes two useful graphic input functions, inputm and gcpmap. The inputm function (analogous to the MATLAB ginput function) allows you to get the latitude-longitude position of a mouse click. The gcpmap function (analogous to the MATLAB function get(gca,'CurrentPoint')) returns the current mouse position, also in latitude and longitude.

Explore inputm with the following commands, which display an axesm-based map with its grid and then request three mouse clicks, the locations of which are stored as geographic coordinates in the variable points. Then the plotm function plots the points you clicked as red markers. The display you see depends on the points you select:

```
axesm sinusoid
framem on; gridm on
points=inputm(3)

points =
    -41.7177 -145.0293
    7.9211    -0.5332
    38.5492    149.2237

plotm(points,'r*')
```



Note If you click outside the map frame, inputm returns a valid but incorrect latitude and longitude, even though the point you indicated is off the map.

One reason you might want to manually identify points on a map is to interactively explore how much distortion a map projection has at given locations. For example, you can feed the data acquired with inputm to the distortcalc function, which computes area and angular distortions at any location on a displayed axesm-based map. If you do so using the points variable, the results of the previous three mouse clicks are as follows:

```
[areascale,angledef] = distortcalc(points(1,1),points(1,2))
areascale =
    1.0000
angledef =
    85.9284

[areascale,angledef] = distortcalc(points(2,1),points(2,2))
```

```
areascale =
    1.0000
angledef =
    3.1143

[areascale,angledef] = distortcalc(points(3,1),points(3,2))
areascale =
    1.0000
angledef =
    76.0623
```

This indicates that the current projection (sinusoidal) has the equal-area property, but exhibits variable angular distortion across the map, less near the equator and more near the poles.

See Also

inputm | gcpmap

Related Examples

• "Create an Interactive Map for Selecting Point Features" on page 4-87


Create an Interactive Map for Selecting Point Features

This example shows how to construct a map of major world cities enhanced with coastlines and terrain. It uses the modified azimuthal Briesemeister map projection. The example includes some optional code that allows a user to interactively pick a location and get the name and location of the nearest city. To see this part of the example, you must run the complete example, pop-out the last illustration into a separate MATLAB figure, and then run the optional code at the MATLAB command line.

Step 1: Set up a Map and Render a Global Elevation Grid


Create an axesm-based map.

```
figure
axesm bries
text(2.8,-1.8,'Briesemeister projection','HorizontalAlignment','right')
framem('FLineWidth',1)
```



Load elevation raster data and a geographic cells reference object. Display the data on the map.


```
load topo60c
geoshow(topo60c, topo60cR, 'DisplayType', 'texturemap')
```



Step 2: Improve the Terrain Display

Apply a colormap appropriate for elevation data. Make the display brighter.


demcmap(topo60c)
brighten(0.5)



Step 3: Add Simplified Coastlines

Load global coastline coordinates. Generalize the coastlines to 0.25-degree tolerance. Then, plot the coastlines in brown.

```
load coastlines
[rlat,rlon] = reducem(coastlat,coastlon,0.25);
geoshow(rlat,rlon,'Color',[.6 .5 .2],'LineWidth',1.5)
```



Step 4: Plot City Locations with Red Point Markers


Read a shapefile containing names of cities worldwide and their coordinates in latitude and longitude.

```
cities = readgeotable('worldcities.shp');
```

Extract the point latitudes and longitudes with extractfield, and add them to the map.

```
lats = cities.Shape.Latitude;
lons = cities.Shape.Longitude
lons = 318 \times 1
  -3.9509
  54.7589
  -0.2121
  35.3894
  38.7575
 138.8528
  44.5408
  72.2474
  30.4098
   3.0397
```

```
'Marker', 'o',...
'MarkerEdgeColor', 'r',...
'MarkerFaceColor', 'r',...
'MarkerSize', 3)
text(-2.8,-1.8,'Major World Cities')
```



Step 5: Select Cities Interactively (Optional)

Now, using the map you've created, you can set up a simple loop to prompt for clicks on the map and display the name and coordinates of the nearest city. You must pop the last map you created in Step 4 into a separate MATLAB figure window, using the button that appears at the top of the map. Also, in the following code, set runCitySelectionLoop to true, and execute the code at the command line.

The code first displays text instructions at the upper left of the map. Then, it enters a loop in which it captures selected latitudes and longitudes with inputm. Use distance to calculate the great circle distance between each selected point and every city in the database. Determine index of the closest city, change the appearance of its marker symbol, and display the city's name and latitude/longitude coordinates.

```
runCitySelectionLoop = false; % Set to true to run optional city selection loop

if(runCitySelectionLoop)
   h1 = text(-2.8, 1.9, 'Click on a dot for its city name. Press ENTER to stop');
   h2 = text(-2.8, 1.7, '');
   h3 = text(-2.8, 1.5, 'City Coordinates.');
   while true
      [selected_lat,selected_lon] = inputm(1);
```

```
if isempty(selected_lat)
              break % User typed ENTER
         end
         d = distance(lats, lons, selected_lat, selected_lon);
         k = find(d == min(d(:)),1);
         city = cities(k,:);
         geoshow(city.Shape.Latitude, city.Shape.Longitude, ...
                   'DisplayType', 'point', ...
'Marker', 'o', ...
'MarkerEdgeColor', 'k', ...
'MarkerFaceColor', 'y', ...
                   'MarkerSize', 3)
        h2.String = city.Name;
        h3.String = num2str([city.Shape.Latitude, city.Shape.Longitude],'%10.2f');
    disp('End of input.')
end
```

See Also

inputm | geoshow | demcmap | shaperead

Create Small Circle and Track Annotations on Maps Interactively

You can generate geographic line annotations, such as navigational tracks and small circles, interactively. Great circle tracks are the shortest distance between points that, when closed, partition the Earth into equal halves. A small circle is the locus of points at a constant distance from a reference point. Use trackg and scircleg to create them by clicking on the map. Double-click the tracks or circles to modify the lines. **Shift+click** the tracks to type specific parameters into a control panel. The control panels also allow you to retrieve or set properties of tracks and circles (for instance, great circle distances and small circle radii).

Set up an orthographic view centered over the Pacific Ocean. Use the coastlines MAT-file.

```
axesm('ortho','origin',[30 180])
framem;
gridm
load coastlines
plotm(coastlat,coastlon,'k')
```


Create a track with the trackg function, which prompts for two endpoints. The default track type is a great circle. Create a great circle track from Los Angeles, California, to Tokyo, Japan, and a 1000 km radius small circle centered on the Hawaiian Islands.

```
trackg
Track1: Click on starting and ending points
```

Now create a small circle around Hawaii with the scircleg function, which prompts for a center point and a point on the perimeter. Make the circle's radius about 2000 km, but don't worry about getting the size exact.

```
scircleg
Circle 1: Click on center and perimeter
```

The map should look approximately like this.



To adjust the size of the small circle to be 2000 km, **Shift+click** anywhere on its perimeter. The Small Circles dialog box appears.

Type 2000 into the Radius field.


Click **Close**. The small circle adjusts to be 2000 km around Hawaii.

To adjust the track between Los Angeles and Tokyo, **Shift+click** on it. This brings up the Track dialog, with which you specify a position and initial azimuth for either endpoint, as well as the length and type of the track.

Change the track type from Great Circle to Rhumb Line with the Track pop-up menu. The track immediately changes shape.

Experiment with the other Track dialog controls. Also note that you can move the endpoints of the track with the mouse by dragging the red circles, and obtain the arc's length in various units of distance.


The following figure shows the Small Circles and Track dialog boxes.



Interactively Display Text Annotations on a Map

Interactively place text annotations on a map using the <code>gtextm</code> function. Call the function by specifying text and optional properties as arguments. Then, choose a location for the text by clicking on the map.

```
gtextm('Hawaii','color','r')
gtextm('Tokyo')
gtextm('Los Angeles')
```



After you place text, you can move it interactively using the selection tool in the map figure window.

To display text on a map by specifying numerical arguments, use the textm function.

Work with Objects by Name

You can manipulate displayed map objects by name. Many Mapping Toolbox functions assign descriptive names to the Tag property of the objects they create. The namem and related functions allow you to control the display of groups of similarly named objects, determine the names and change them if desired, and use the name in the set and get functions.


Some mapping display functions like framem, gridm, and contourm assign object tags by default. You can also set the name upon display by assigning a value to the Tag property in mapping display functions that use property name/property value pairs. If the Tag does not contain a value, the name defaults to an object's Type property, such as 'line' or 'text'.

Manipulate Displayed Map Objects By Name

This example shows how to manipulate objects displayed on <code>axesm</code>-based maps by name. Many functions assign descriptive names to the <code>Tag</code> property of the objects they create. The <code>namem</code> and related functions allow you to control the display of groups of similarly named objects, determine the names and change them, if desired, and use the name in calls to <code>get</code> and <code>set</code>.

Display a vector map of the world.

```
f = axesm('fournier')
f =
  Axes with properties:
             XLim: [0 1]
             YLim: [0 1]
           XScale: 'linear'
           YScale: 'linear'
    GridLineStyle: '-'
         Position: [0.1300 0.1100 0.7750 0.8150]
            Units: 'normalized'
  Show all properties
framem on;
gridm on;
plabel on;
mlabel('MLabelParallel',0)
load coastlines
plotm(coastlat,coastlon,'k','Tag','Coastline')
```




List the names of the objects in the current ${\tt axesm\hbox{-}based}$ map using ${\tt namem}$.

namem

```
ans = 6x9 char array
    'PLabel '
    'MLabel '
    'Parallel '
    'Meridian '
    'Coastline'
    'Frame '
```


Use handlem to get the handles to the graphics objects displayed on an <code>axesm</code>-based map. You use these handles to get or set object properties. For example, change the line width of the coastline with <code>set</code> . If you call <code>handlem</code> with no arguments, it opens a graphical user interface that lists all the objects on the map. You can select objects interactively.

```
set(handlem('Coastline'),'LineWidth',2)
```




Change the colors of the meridian and parallel labels separately.

```
set(handlem('Mlabel'),'Color',[.5 .2 0])
set(handlem('Plabel'),'Color',[.2 .5 0])
```



Change the color of the labels to be the same.

```
setm(f,'fontcolor', [.4 .5 .6])
```



Use handlem specifying the 'all' modifier to get a list of all text objects or all line objects.

```
t = handlem('alltext')
```

```
t =
  26x1 Text array:
  Text
           (PLabel)
           (PLabel)
  Text
  Text
           (PLabel)
           (PLabel)
  Text
           (PLabel)
  Text
           (PLabel)
  Text
  Text
           (PLabel)
  Text
           (PLabel)
  Text
           (PLabel)
           (PLabel)
  Text
  Text
           (PLabel)
  Text
           (PLabel)
           (PLabel)
  Text
  Text
           (MLabel)
           (MLabel)
  Text
```

```
Text
          (MLabel)
 Text
          (MLabel)
          (MLabel)
 Text
 Text
          (MLabel)
          (MLabel)
 Text
l = handlem('allline')
l =
 3x1 Line array:
        (Parallel)
 Line
         (Meridian)
 Line
 Line
          (Coastline)
```

Making Three-Dimensional Maps

- "Sources of Terrain Data" on page 5-2
- "Determine and Visualize Visibility Across Terrain" on page 5-3
- "Visualize Viewsheds and Coverage Maps Using Terrain" on page 5-5
- "Add Light Source to Terrain Map" on page 5-35
- "Surface Relief Shading" on page 5-38
- "Colored Surface Shaded Relief" on page 5-43
- "Relief Mapping with Light Objects" on page 5-47
- "Drape Data on Elevation Maps" on page 5-55
- "Drape Geoid Heights over Topography" on page 5-60
- "Combine Dissimilar Grids by Converting Regular Grid to Geolocated Data Grid" on page 5-65
- "Access Basemaps and Terrain for Geographic Globe" on page 5-68
- "Create Interactive Basemap Picker" on page 5-70
- "Visualize Aircraft Line-of-Sight over Terrain" on page 5-72
- "Visualize UAV Flight Path on 2-D and 3-D Maps" on page 5-81

Sources of Terrain Data

Nearly all published terrain elevation data is in the form of data grids. "Types of Data Grids and Raster Display Functions" on page 4-58 described basic approaches to rendering surface data grids with Mapping Toolbox functions, including viewing surfaces in 3-D axes. The following sections describe some common data formats for terrain data, and how to access and prepare data sets for particular areas of interest.

Digital Terrain Elevation Data from NGA

The Digital Terrain Elevation Data (DTED) Model is a series of gridded elevation models with global coverage at resolutions of 1 kilometer or finer. DTED files are products of the U. S. National Geospatial Intelligence Agency (NGA), formerly the National Imagery and Mapping Agency (NIMA), and before that, the Defense Mapping Agency (DMA). The data is provided as 1-by-1 degree tiles of elevations on geographic grids with product-dependent grid spacing. In addition to NGA's own DTED files, terrain data from Shuttle Radar Topography Mission (SRTM), a cooperative project between NASA and NGA, are also available in DTED format, levels 1 and 2 (see below).

The lowest resolution data is the DTED Level 0, with a grid spacing of 30 arc-seconds, or about 1 kilometer. The DTED files are binary. The files have file names with the extension dtN, where N is the level of the DTED product. You can find published specifications for DTED at the NGA website.

NGA also provides higher resolution terrain data files. DTED Level 1 has a resolution of 3 arcseconds, or about 100 meters, increasing to 18 arc-seconds near the poles. It was the primary source for the USGS 1:250,000 (1 degree) DEMs. Level 2 DTED files have a minimum resolution of 1 arcsecond near the equator, increasing to 6 arc-seconds near the poles. DTED files are available on from several sources on CD-ROM, DVD, and on the Internet.

Note For information on locating map data for download over the Internet, see the following documentation at the MathWorks website: "Find Geospatial Data Online" on page 2-77.

Digital Elevation Model Files from USGS

The United States Geological Survey (USGS) has prepared terrain data grids for the U.S. suitable for use at scales between 1:24,000 and 1:250,000 and beyond. Some of this data originated from Defense Mapping Agency DTED files. Specifications and data quality information are available for these digital elevation models (DEMs) and other U.S. National Mapping Program geodata from the USGS. USGS no longer directly distributes 1:24,000 DEMs and other large-scale geodata. U.S. DEM files in SDTS format are available from private vendors, either for a fee or at no charge, depending on the data sets involved.

The largest scale USGS DEMs are partitioned to match the USGS 1:24,000 scale map series. The grid spacing for these elevations models is 30 meters on a Universal Transverse Mercator grid. Each file covers a 7.5-minute quadrangle. (Note, however, that only a subset of paper quadrangle maps are projected with UTM, and that USGS vector geodata products might not use this coordinate system.) The map and data series is available for much of the conterminous United States, Hawaii, and Puerto Rico.

Determine and Visualize Visibility Across Terrain

You can use regular data grids of elevation data to answer questions about the mutual visibility of locations on a surface (intervisibility). For example,

- Is the line of sight from one point to another obscured by terrain?
- What area can be seen from a location?
- · What area can see a given location?

The first question can be answered with the los2 function. In its simplest form, los2 determines the visibility between two points on the surface of a digital elevation map. You can also specify the altitudes of the observer and target points, as well as the datum with respect to which the altitudes are measured. For specialized applications, you can even control the actual and effective radius of the Earth. This allows you to assume, for example, that the Earth has a radius 1/3 larger than its actual value, a setting which is frequently used in modeling radio wave propagation.

Compute Line of Sight

The following example shows a line-of-sight calculation between two points on a regular data grid generated by the peaks function. The calculation is performed by the los2 function, which returns a logical result: 1 (points are mutually visible—intervisible), or 0 (points are not intervisible).

Create an elevation grid using peaks with a maximum elevation of 500, and set its origin at (0°N, 0°W), with a spacing of 1000 cells per degree):

```
map = 500*peaks(100);
maplegend = [ 1000 0 0];
```


2 Define two locations on this grid to test intervisibility:

```
lat1 = -0.027;
lon1 = 0.05;
lat2 = -0.093;
lon2 = 0.042;
```

Calculate intervisibility. The final argument specifies the altitude (in meters) above the surface of the first location (lat1, lon1) where the observer is located (the viewpoint):

```
los2(map,maplegend,lat1,lon1,lat2,lon2,100)
ans =
```

1



The los2 function produces a profile diagram in a figure window showing visibility at each grid cell along the line of sight that can be used to interpret the Boolean result. In this example, the diagram shows that the line between the two locations just barely clears an intervening peak.

You can also compute the *viewshed*, a name derived from *watershed*, which indicates the elements of a terrain elevation grid that are visible from a particular location. The *viewshed* function checks for a line of sight between a fixed observer and each element in the grid. See the *viewshed* function reference page for an example.

Visualize Viewsheds and Coverage Maps Using Terrain

Display viewsheds and coverage maps for a region of interest using satellite imagery and terrain data. A *viewshed* includes areas that are within line of sight (LOS) of a set of points, and a *coverage map* includes received power for the areas within range of a set of wireless transmitters. You can use a viewshed as a first-order approximation of a coverage map.

By combining the mapping capabilities in Mapping ToolboxTM with the RF propagation capabilities in Antenna ToolboxTM, you can create contoured coverage maps and use the contour data for both visualization and analysis. This example shows you how to:

- View imagery and terrain on 2-D maps
- View imagery, terrain, and viewsheds on 3-D relief maps
- View coverage maps in 2-D using contour plots and bar graphs
- Determine whether nearby points are within coverage
- View coverage maps for other regions of interest

View Imagery on 2-D Map

You can view imagery for a region of interest by plotting data into geographic axes. Geographic axes enable you to plot 2-D data over basemaps, explore regions interactively, and add data tips to points of interest.

Specify the geographic coordinates and heights of two cell towers in the San Fernando Valley region. Specify the heights using meters above the terrain.

```
lat1 = 34.076389;
lon1 = -118.468944;
towerHeight1 = 17.1;
text1 = "Tower 1";
lat2 = 34.386389;
lon2 = -118.329778;
towerHeight2 = 30.5;
text2 = "Tower 2";
```

Display the locations of the cell towers over a satellite basemap.

```
figure
basemap = "satellite";
geobasemap(basemap)

geoplot([lat1 lat2],[lon1 lon2], ...
    LineStyle="none",Marker="o",MarkerSize=10, ...
    MarkerEdgeColor="k",MarkerFaceColor="c")
```

Prepare to create a 3-D relief map for the same region by querying the zoom level, latitude limits, and longitude limits of the geographic axes. To ensure that the relief map covers the same region, change the zoom level of the geographic axes to an integer.


```
gx = gca;
zoomLevel = floor(gx.ZoomLevel);
gx.ZoomLevel = zoomLevel;
```

```
[latlim,lonlim] = geolimits(gx);
```

Customize the map by labeling the cell towers and adding a title.

```
txtDelta = 0.005;
text(lat1 + txtDelta,lon1 + txtDelta,text1,Color="w")
text(lat2 + txtDelta,lon2 + txtDelta,text2,Color="w")
title("Satellite Imagery of San Fernando Valley Region")
subtitle("With Placement of Cell Towers")
```

Satellite Imagery of San Fernando Valley Region



View Terrain on 2-D Map

Visualize the terrain for the same region of interest by plotting imported elevation data into an axesm-based map. axesm-based maps enable you to display geographic data using a map projection.

Read Terrain Elevation Data

Read terrain elevation data for the region of interest from a Web Map Service (WMS) server. WMS servers provide geospatial data such as elevation, temperature, and weather from web-based sources.

Search the WMS Database for terrain elevation data hosted by MathWorks®. The wmsfind function returns search results as layer objects. A *layer* is a data set that contains a specific type of geographic information, in this case elevation data.

```
layer = wmsfind("mathworks",SearchField="serverurl");
layer = refine(layer,"elevation");
```

Read the elevation data from the layer into the workspace as an array and a spatial reference object in geographic coordinates. Get quantitative data by specifying the image format as BIL.

```
[Z,RZ] = wmsread(layer,Latlim=latlim,Lonlim=lonlim,ImageFormat="image/bil");
```

Prepare the elevation data for plotting by converting the data type to double.

```
Z = double(Z);
```


Find Tower Elevations

Calculate the terrain elevation at the base of each cell tower. The elevations are in meters above mean sea level.

```
height1 = geointerp(Z,RZ,lat1,lon1,"nearest")
height1 = 177
height2 = geointerp(Z,RZ,lat2,lon2,"nearest")
height2 = 1422
```

Visualize Elevation and Tower Locations

Create an axesm-based map with an appropriate projection for the region. Then, display the elevation data as a surface using an appropriate colormap. Note that the areas of highest elevation are in the northeast corner.



View Imagery, Terrain, and Viewshed on 3-D Relief Map

Visualize the imagery, terrain, and viewshed for the region by plotting the terrain data over a basemap image in a standard axes. Basemap images enable you to provide geographic context for plot types that geographic axes do not support, such as 3-D surfaces.

Read Basemap Image

Read a basemap image using the same basemap, geographic limits, and zoom level as the geographic axes. The readBasemapImage function reads the image into the workspace as an array, a spatial reference object in Web Mercator (WGS 84/Pseudo-Mercator) coordinates, and an attribution string.

```
[A,RA,attrib] = readBasemapImage(basemap,latlim,lonlim,zoomLevel);
```

To display the cell tower locations over the basemap image, you must first project the geographic coordinates to Web Mercator coordinates.

```
proj = RA.ProjectedCRS;
[x1,y1] = projfwd(proj,lat1,lon1);
[x2,y2] = projfwd(proj,lat2,lon2);
```

Plot the projected coordinates over the basemap image. Note that this visualization is similar to the geographic axes visualization.

```
figure
axis off
hold on
```

```
mapshow(A,RA)
plot([x1 x2],[y1 y2], ...
    LineStyle="none",Marker="o",MarkerSize=10, ...
    MarkerEdgeColor="k",MarkerFaceColor="c")

txtDeltaXY = 500;
text(x1 + txtDeltaXY,y1 + txtDeltaXY,text1,Color="w")
text(x2 + txtDeltaXY,y2 + txtDeltaXY,text2,Color="w")
title("Satellite Basemap Imagery of San Fernando Valley Region")
subtitle("Attribution: " + attrib)
```

Satellite Basemap Imagery of San Fernando Valley Region

Attribution: Earthstar Geographics



Calculate Viewsheds from Towers

Read the terrain data again, this time using array dimensions and geographic limits that match the dimensions and limits of the basemap image.

Calculate the viewshed for each tower by specifying the terrain data and the cell tower coordinates. The first argument returned by each viewshed call indicates visible areas using 1 values and obscured areas using 0 values.

```
[vis1,visR1] = viewshed(Z,RZ,lat1,lon1,towerHeight1);
[vis2,visR2] = viewshed(Z,RZ,lat2,lon2,towerHeight2);
```

Calculate the combined viewshed for both towers. To avoid plotting the obscured areas, replace the θ values with NaN values.

```
visCombined = vis1 | vis2;
vis = visCombined;
vis = double(vis);
vis(vis == 0) = NaN;
visR = visR2;
```

Extract the geographic coordinates of the elevation data from its spatial reference object. Then, project the coordinates to Web Mercator coordinates.

```
[latz,lonz] = geographicGrid(RZ);
[xz,yz] = projfwd(proj,latz,lonz);
```

View Individual and Combined Viewsheds

Display the viewshed for each tower and the combined viewshed for both towers in a tiled layout.

Define a colormap for the viewshed. Use turquoise for visible areas and black for obscured areas.

```
cmapt = [0 0 0];
covcolor = [0.1034  0.8960  0.7150];
cmapt(2,:,:) = covcolor;
```

Create a tiled layout. Display the viewshed for the individual towers on the left.

```
figure
clim([0 1])
colormap(cmapt)
tiledlayout(2,3,Padding="tight",TileSpacing="tight")

nexttile
geoshow(vis1,visR1,EdgeColor="none",DisplayType="surface")
axis off
title("Viewshed")
subtitle("Tower 1")

nexttile(4)
geoshow(vis2,visR2,EdgeColor="none",DisplayType="surface")
axis off
title("Viewshed")
subtitle("Tower 2")
```


Display the basemap image and the combined viewshed on the right. Specify the z-coordinates for the labels using the terrain height (above mean sea level) and the tower height (above the terrain).

```
nexttile([2,2])
mapshow(A,RA)
hold on
mapshow(xz,yz,vis,EdgeColor="none",DisplayType="surface")
axis off

zdelta = 150;
z1 = height1 + towerHeight1 + zdelta;
```

```
z2 = height2 + towerHeight2 + zdelta;
text(x1,y1,z1,text1,Color="k",EdgeColor="k",BackgroundColor="w")
text(x2,y2,z2,text2,Color="k",EdgeColor="k",BackgroundColor="w")
title("Combined Viewshed Over Basemap Image")
subtitle("Attribution: " + attrib)
```

Viewshed Tower 1



Viewshed Tower 2

View Basemap Image and Viewshed on 3-D Relief Map

Prepare the combined viewshed for plotting.

- Find the indices of visible areas in the combined viewshed.
- Replace the visible areas in the combined viewshed with the terrain data (the corresponding values of Z).

```
[row,col] = find(visCombined);
sz = size(visCombined);
ind = sub2ind(sz,row,col);
vis(ind) = Z(ind);
```

Create a new figure that uses the same colormap as the tiled layout. Remove the axes lines and enable the plot to extend to the edges of the axes.

```
figure
colormap(covcolor)
hold on
```

```
axis off axis tight
```


Visualize the basemap image, viewshed, and terrain using surfaces.

- Display the terrain by draping the basemap image over the elevation data. Specify the z-coordinates using the terrain data, and specify the surface colors using the image data.
- Display the combined viewshed.
- Customize the plot by adding text labels and a title.
- View the plot in 3-D. Adjust the data aspect ratio so that elevation scale is comparable to the *xy*-scale.

```
mapshow(xz,yz,Z,DisplayType="surface",CData=A)
mapshow(xz,yz,vis,EdgeColor="none",DisplayType="surface")
text(x1,y1,z1,text1,Color="k",EdgeColor="k",BackgroundColor="w")
text(x2,y2,z2,text2,Color="k",EdgeColor="k",BackgroundColor="w")
title("Satellite Basemap Imagery with Terrain and Viewshed")
subtitle("Attribution: " + attrib)
daspect([1 1 0.25])
view(3)
```

Satellite Basemap Imagery with Terrain and Viewshed

Attribution: Earthstar Geographics



Visualize Coverage Maps in 2-D

A viewshed is comparable to a wireless coverage map that includes only line-of-sight (LOS) propagation. You can create more detailed coverage maps and calculate received power by using transmitter antenna sites and propagation models.

Calculate Coverage Map

Create a transmitter site for each cell tower. Then, calculate the coverage map and return the result as a propagationData object. By default, the coverage function uses a Longley-Rice propagation model and incorporates diffraction over terrain.

```
txTower1 = txsite(Name=text1,Latitude=lat1,Longitude=lon1);
txTower2 = txsite(Name=text2,Latitude=lat2,Longitude=lon2);
txsites = [txTower1; txTower2];
pd = coverage(txsites);
```

Extract latitude and longitude values, power values, and power levels from the propagationData object by using the propagationDataGrid on page 5-28 helper function. Find the limits of the quadrangle that bounds the coverage map.

```
dataVariableName = "Power";
maxrange = [30000 30000];
[lats,lons,data,levels] = propagationDataGrid(pd,dataVariableName,maxrange,txsites);
[covlatlim,covlonlim] = geoquadline(lats,lons);
```


Define a colormap using the power levels. Create a new figure that uses the power levels colormap.

```
cmap = turbo(length(levels));
climLevels = [min(levels) max(levels)+10];
figure
colormap(cmap)
clim(climLevels)
hold on
```

Create an axesm-based map with an appropriate projection for the region. Display the coverage map, a rectangle that represents the San Fernando Valley region, and the transmitter sites on the map. Note that the coverage map extends beyond the San Fernando Valley region.

```
usamap(covlatlim,covlonlim)
geoshow(lats,lons,data,DisplayType="surface")
geoshow(latlim([1 2 2 1 1]),lonlim([1,1,2,2,1]),Color="k")
textm(lat1,lon1,text1,Color="k",FontSize=12)
textm(lat2,lon2,text2,Color="k",FontSize=12)
title("Coverage Map with Boundary of Basemap Image")

cb = colorbar;
cb.Label.String = "Power (dBm)";
cb.Ticks = levels;
```



View Contoured Coverage Map on Basemap Image

Project the geographic coordinates of the coverage map to Web Mercator coordinates.

```
[cx,cy] = projfwd(proj,lats,lons);
```

Create a figure that uses the power levels colormap.

```
figure
colormap(cmap)
clim(climLevels)
axis off
hold on
```

Contour the coverage map, specifying the contour levels as the power levels, and display the result over the basemap image. Change the limits of the map to match the San Fernando Valley region.


```
mapshow(A,RA)
contourf(cx,cy,data,LevelList=levels)

xlim(RA.XWorldLimits)
ylim(RA.YWorldLimits)

text(x1,y1,text1,Color="w")
text(x2,y2,text2,Color="w")
title("Contoured Coverage Map Over Basemap Image")
subtitle("Attribution: " + attrib)
```

```
cb = colorbar;
cb.Label.String = "Power (dBm)";
cb.Ticks = levels;
```

Contoured Coverage Map Over Basemap Image



View Contoured Coverage Map and Viewshed on Basemap Image

Project the geographic coordinates of the combined viewshed to Web Mercator coordinates.

```
[vlat,vlon] = geographicGrid(visR);
[vx,vy] = projfwd(proj,vlat,vlon);
```

Display the coverage map and viewshed over the basemap image by using contour plots. You can create a map with two colorbars by overlaying two axes objects.


Use the first axes to display the basemap image, the coverage map, and a colorbar for the coverage map.

```
figure
ax1 = axes;
hold(ax1,"on")
axis(ax1,"off")
clim(ax1,climLevels)
colormap(ax1,cmap)

mapshow(ax1,A,RA)
contourf(ax1,cx,cy,data,LevelList=levels);
xlim(ax1,RA.XWorldLimits)
```


```
ylim(ax1,RA.YWorldLimits)
title(ax1, "Contoured Coverage Map and Viewshed on Basemap Image")
subtitle(ax1,"Attribution: " + attrib)
cb1 = colorbar(ax1);
cb1.Label.String = "Power (dBm)";
cb1.Ticks = levels;
Use the second axes to display the viewshed and a colorbar for the viewshed.
ax2 = axes(Visible="off");
hold(ax2, "on")
colormap(ax2,covcolor)
[~,visContourMap] = contourf(ax2,vx,vy,vis,LevelList=0.5:1:1.5);
cb2 = colorbar(ax2);
cb2.Label.String = "Viewshed";
cb2.Ticks = [];
Reposition the axes objects and the colorbars.
ax1.Position = [ax1.Position(1) ax1.Position(2)-0.04 ax1.Position(3) ax1.Position(4)];
ax2.Position = ax1.Position;
cb1.Position = [cb1.Position(1) cb1.Position(2) cb1.Position(3) cb1.Position(4)*0.8];
cb2.Position = [cb2.Position(1) 0.76 cb2.Position(3) 0.1];
```

Contoured Coverage Map and Viewshed on Basemap Image



In addition to LOS analysis, the coverage map incorporates diffraction over terrain. As a result, the coverage map extends beyond the viewshed.

Adjust the transparency of the viewshed. When you decrease the value of faceAlpha, the viewshed becomes more transparent and you can see the coverage map beneath.



View Contoured Coverage Map on Geographic Axes

To display a contoured coverage map over geographic axes, contour the coverage map using the <code>contourDataGrid</code> on page 5-29 helper function. Each row of the returned geospatial table corresponds to a power level and includes the contour shape, the area of the contour shape in square kilometers, the minimum power for the level, and the power range for the level. The area value for each contour shape includes the regions that are covered by other contour shapes.

GT = contourDataGrid(lats,lons,data,levels);
disp(GT)

Shape	Area (sq km)	Power (dBm)	Power Range (dBm)	
geopolyshape	2.5889e+06	-120	- 120	- 110
geopolyshape	2.314e+06	-110	- 110	- 100
geopolyshape	2.1344e+06	-100	- 100	- 90

geopolyshape	1.7129e+06	- 90	-90	-80
geopolyshape	3.0979e+05	- 80	-80	-70
geopolyshape	13563	-70	-70	-60
geopolyshape	1894.9	- 60	-60	-50
geopolyshape	676.29	- 50	-50	-40

Plot the contoured coverage map and a rectangle that represents the San Fernando Valley region into geographic axes.


```
figure
geobasemap satellite
colormap(cmap)
clim(climLevels)
hold on

hp = geoplot(GT,ColorVariable="Power (dBm)",EdgeColor="k",FaceAlpha=1);
boundary = geoplot(latlim([1 2 2 1 1]),lonlim([1,1,2,2,1]),Color="k",LineWidth=2);

text(lat1,lon1,text1,Color="w")
text(lat2,lon2,text2,Color="w")
title("Contoured Coverage Map with Boundary of Basemap Image")


cb = colorbar;
cb.Label.String = "Power (dBm)";
cb.Ticks = levels;
```

Contoured Coverage Map with Boundary of Basemap Image




Zoom the map into the San Fernando Valley region and delete the boundary.

geolimits(latlim,lonlim)
delete(boundary)
title("Contoured Coverage Map at Boundary of Basemap Image")



Adjust the transparency of the coverage map. When you decrease the value of faceAlpha, the coverage map becomes more transparent and you can see the basemap beneath.




View Bar Graph of Coverage Area

Create a bar graph that shows the coverage area in square kilometers for each power level. As the power level increases, the coverage area decreases.

```
figure
colormap(cmap)
clim(climLevels)
hold on

bar(GT.("Power (dBm)"),GT.("Area (sq km)"),FaceColor="flat",CData=cmap);
ylabel("Area in square kilometers")
xlabel("Power (dBm)")

cb = colorbar;
cb.Label.String = "Power (dBm)";
cb.Ticks = levels;
```



Determine If Points Are Within Coverage

Determine whether points within the San Fernando Valley region are within coverage.

Calculate Coverage at Point Locations

Specify the locations of two points near the cell towers. Determine whether the points are within coverage by using the incoverage on page 5-32 helper function. The result indicates the first point is in coverage and the second point is not in coverage.

```
locationLats = [34.2107 34.1493];
locationLons = [-118.4545 -118.1744];

[tf,powerLevels] = incoverage(locationLats,locationLons,GT);
disp(tf)


1
0
```

Display the power levels. The result -Inf indicates that the second point is not in coverage.

disp(powerLevels)

-90 -Inf

Display the point that is in coverage using a cyan marker and the point that is not in coverage using a black marker.



Interactively Select Points and Calculate Coverage at Point Locations

Select points and determine whether they are in coverage.

Set up a map that uses the power levels colormap. Then, plot the contoured coverage map.

```
figure
geobasemap topographic
geolimits(latlim,lonlim)
geotickformat dd
hold on
colormap(cmap)
clim(climLevels)

contourPlot = geoplot(GT,ColorVariable="Power (dBm)",EdgeColor="k",FaceAlpha=1);
cb = colorbar;
```

```
cb.Label.String = "Power (dBm)";
cb.Ticks = levels(1:end);
```


Select the points. Use predefined points by specifying interactivelySelectPoints as false. Alternatively, you can interactively select points by specifying interactivelySelectPoints as true. Specify the number of points to interactively select by specifying a value for numberOfPoints.

Determine whether each point is within coverage. If the point is not within coverage, display it on the map in black. If the point is within coverage, display it on the map using the color associated with its power level.

```
for k = 1:size(pts,1)
    latpoint = pts(k,1);
    lonpoint = pts(k,2);
    [tf,powerLevel] = incoverage(latpoint,lonpoint,GT);


if ~tf
    color = [0 0 0];
    else
        index = GT.("Power (dBm)") == powerLevel;
        color = cmap(index,:,:);
    end

    h = geoplot(latpoint,lonpoint,"o",MarkerEdgeColor=color,MarkerFaceColor=color,MarkerSize=10)
    dt = datatip(h);
    dtrow = dataTipTextRow("Power",powerLevel);
    h.DataTipTemplate.DataTipRows(end+1) = dtrow;
end
title("Selected Points")
```



Toggle off the contour plot by setting showContourPlot to false. The color of each point indicates its power level.

```
showContourPlot = false
contourPlot.Visible = showContourPlot;
```



Create Geographic Coverage Maps for Other Regions


The **geocoverage** on page 5-32 helper function calculates or displays a coverage map for the specified transmitter sites. When you specify an output argument, the function returns a geospatial table.

T = geocoverage(txsites);
disp(T)


Shape	Area (sq km)	Power (dBm)	Power Range (dBm)	
geopolyshape	2.5889e+06	-120	-120	-110
geopolyshape	2.314e+06	-110	-110	- 100
geopolyshape	2.1344e+06	-100	-100	-90
geopolyshape	1.7129e+06	- 90	-90	-80
geopolyshape	3.0979e+05	-80	-80	-70
geopolyshape	13563	- 70	-70	-60
geopolyshape	1894.9	- 60	-60	- 50
geopolyshape	676.29	- 50	-50	-40

When you omit the output argument, the function contours the coverage map and displays the result over a basemap.

```
basemap = "topographic";
geocoverage(txsites(1),basemap)
```




You can use the <code>geocoverage</code> helper function to create coverage maps for other locations. For example, create a coverage map for cell towers near Boston. The <code>geocoverage</code> function calculates coverage data for up to 30 kilometers from the transmitter sites.



The cell towers are close together. View the area immediately around the towers by zooming in on the coverage map.

```
gx = gca;
gx.ZoomLevel = 12;
```



Helper Functions

The propagationDataGrid helper function extracts the latitude and longitude values clats and clons, the power values cdata, and the power levels levels from the propagation data object pd with data variable dataVariableName, using the transmitter sites txsites and the maximum range in meters from the transmitter sites maxrange. Within the function:

- Create regularly spaced grids of latitude and longitude values from the propagation data object.
- Determine which latitude and longitude values are within range of the transmitter sites.
- Create a grid of power values by interpolating the propagation data. Interpolate only the values that are within range of the transmitter sites.
- Determine the power levels by discretizing the data grid.

function [clats,clons,cdata,levels] = propagationDataGrid(pd,dataVariableName,maxrange,txsites)
% Extract propagation data grid from propagationData object

```
% Create grids of latitude and longitude values
imageSize = [512 512];
lats = pd.Data.Latitude;
lons = pd.Data.Longitude;
data = pd.Data.(dataVariableName);
[lonmin,lonmax] = bounds(lons);
[latmin,latmax] = bounds(lats);
```

```
lonsv = linspace(lonmin.lonmax.imageSize(2)):
    latsv = linspace(latmin,latmax,imageSize(1));
    [clons,clats] = meshgrid(lonsv,latsv);
   % Determine which latitude and longitude values are within range of the
   % transmitters
   txlat = [txsites.Latitude]';
   txlon = [txsites.Longitude]';
   numTx = size(txlat.1):
   gc = nan(numel(clons), numTx);
    for txInd = 1:numTx
        qc(:,txInd) = distance(txlat(txInd),txlon(txInd),clats(:),clons(:),wgs84Ellipsoid);
   end
   isInRange = any(gc <= maxrange,2);</pre>
   % Create grid of power values
    cdata = nan(imageSize);
    cdata(isInRange) = interp(pd,clats(isInRange),clons(isInRange), ...
        DataVariableName=dataVariableName);
   % Determine power levels
    [bmin.bmaxl = bounds(data):
    levels = max(bmin,-120):10:bmax;
   datalevels = sort(levels);
   maxBin = max(max(datalevels(:)), max(cdata(:))) + 1; % Need max bin edge to include all value
   bins = [datalevels(:); maxBin];
    cdata = discretize(cdata,bins,datalevels);
end
```

The contourDataGrid helper function contours a data grid created using the propagationDataGrid helper function and returns the result as a geospatial table. Each row of the table corresponds to a power level and includes the contour shape, the area of the contour shape in square kilometers, the minimum power for the level, and the power range for the level. Within the function:

- Ensure that the function contours power values below the minimum power level by replacing NaN values in the power grid with a large negative number.
- Calculate accurate areas by projecting the latitude and longitude coordinates using an equal-area projection, in this case the North America Albers Equal Area Conic projection.
- Contour the projected coordinates using the contourf function. Specify the contour levels as the power levels. The contourf function returns a matrix that contains, for each power level, the coordinates of the contour lines.
- Prepare to analyze the data for each contour line by initializing several variables.
- Calculate the area within each contour line. Remove areas that correspond to holes and ignore negative areas. Unproject the coordinates.
- Create contour shapes from the unprojected coordinates. Include the contour shapes, the areas, and the power levels in a geospatial table.
- Condense the geospatial table into a new geospatial table with one row per power level. Each row contains one combined contour shape (that includes all contour shapes for the power level), the area of the combined contour shape, the minimum power for the level, and the power range for the level.

 Clean up the geospatial table. Convert the area of each shape to square kilometers, ensure that small contours appear on top of large contours by sorting the rows, and rename the table variables.

```
function GT = contourDataGrid(latd,lond,data,levels)
% Contour data grid created from propagationDataGrid helper function
    % Replace NaN values in power grid with a large negative number
   data(isnan(data)) = min(levels) - 1000;
   % Project the coordinates using an equal-area projection
    proj = projcrs(102008, "Authority", "ESRI");
    [xd,yd] = projfwd(proj,latd,lond);
   % Contour the projected data
    fig = figure("Visible", "off");
   obj = onCleanup(@()close(fig));
    c = contourf(xd,yd,data,LevelList=levels);
    % Initialize variables
   x = c(1,:);
   y = c(2,:);
    n = length(y);
    k = 1:
   index = 1;
    levels = zeros(n,1);
    latc = cell(n,1);
    lonc = cell(n,1);
   Area = zeros(n,1);
   % Calculate the area within each contour line. Remove areas that
   % correspond to holes and ignore negative areas.
   while k < n
        level = x(k);
        numVertices = y(k);
        vk = v(k+1:k+numVertices);
        xk = x(k+1:k+numVertices);
        k = k + numVertices + 1;
        [first,last] = findNanDelimitedParts(xk);
        jindex = 0;
        jy = {};
        jx = \{\};
        sumpart = 0;
        for j = 1:numel(first)
            % Process the j-th part of the k-th level
            s = first(j);
            e = last(j);
            cx = xk(s:e);
            cy = yk(s:e);
            if cx(end) \sim cx(1) \& cy(end) \sim cy(1)
                cy(end+1) = cy(1); %#ok<*AGROW>
                cx(end+1) = cx(1);
            end
            if j == 1 && ~ispolycw(cx,cy)
```

```
% First region must always be clockwise
            [cx,cy] = poly2cw(cx,cy);
        end
        jindex = jindex + 1;
        jy{jindex,1} = cy(:)';
        jx\{jindex,1\} = cx(:)';
        a = polyarea(cx,cy);
        if ~ispolycw(cx,cy)
            % Remove areas that correspond to holes
            a = -a:
        end
        sumpart = sumpart + a;
    end
    % Add a part when its area is greater than 0. Unproject the
    % coordinates.
    [jx,jy] = polyjoin(jx,jy);
    if length(jy) > 2 && length(jx) > 2 && sumpart > 0
        [jlat,jlon] = projinv(proj,jx,jy);
        latc{index,1} = jlat(:)';
        lonc{index,1} = jlon(:)';
        levels(index,1) = level;
        Area(index,1) = sumpart;
        index = index + 1;
    end
end
% Create contour shapes from the unprojected coordinates. Include the
% contour shapes, the areas, and the power levels in a geospatial
% table.
latc = latc(1:index-1);
lonc = lonc(1:index-1);
Shape = geopolyshape(latc,lonc);
Area = Area(1:index-1);
levels = levels(1:index-1);
Levels = levels;
allPartsGT = table(Shape, Area, Levels);
% Condense the geospatial table into a new geospatial table with one
% row per power level.
GT = table.empty;
levels = unique(allPartsGT.Levels);
for k = 1:length(levels)
    gtLevel = allPartsGT(allPartsGT.Levels == levels(k),:);
    tLevel = geotable2table(gtLevel,["Latitude","Longitude"]);
    [lon,lat] = polyjoin(tLevel.Longitude,tLevel.Latitude);
    Shape = geopolyshape(lat,lon);
    Levels = levels(k);
    Area = sum(gtLevel.Area);
    GT(end+1,:) = table(Shape, Area, Levels);
end
```

The incoverage helper function determines whether the points with latitude values lat and longitude values lon are within the coverage map defined by the geospatial table T. Within the function:

- Determine whether the points are within the coverage map and return the results in in. The elements of in are 1 (true) when the corresponding points are within coverage.
- Determine the power levels for the points and return the results in powerLevels. A value of -Inf indicates that the corresponding point is not within coverage.

```
function [in,powerLevels] = incoverage(lat,lon,T)
% Query points in coverage
    % Determine whether points are within coverage
   tf = false(length(T.Shape),length(lat));
    for k = 1:length(T.Shape)
        tf(k,:) = isinterior(T.Shape(k), geopointshape(lat,lon));
   % Determine the power levels for the points
    in = false(length(lat),1):
    powerLevels = -inf(length(lat),1);
    for k = 1:length(in)
        v = tf(:,k);
        in(k) = any(v);
        if in(k)
            powerLevels(k) = max(T{v,"Power (dBm)"});
        end
   end
end
```

The geocoverage helper function calculates or displays a coverage map for the transmitter sites txsites. Within the function:

- Calculate the coverage map by using the coverage function. Then, contour the coverage map by using the progagationDataGrid and contourDataGrid helper functions.
- When you do not specify an output argument, the function displays the contoured coverage map over geographic axes using the basemap basemap.
- When you do specify an output argument, the function returns the result as a geospatial table.

```
function varargout = geocoverage(txsites,basemap)
% Display or calculate contoured coverage map
```

```
% Calculate and contour the coverage map
   pd = coverage(txsites);
   dataVariableName = "Power";
   maxrange = 30000*ones(1,length(txsites));
    [lats,lons,data,levels] = propagationDataGrid(pd,dataVariableName,maxrange,txsites);
   GT = contourDataGrid(lats,lons,data,levels);
   % If you do not specify an output argument, display the coverage map
   if nargout == 0
        if nargin < 2
            basemap = "satellite";
        cmap = turbo(length(levels));
        figure
        geobasemap(basemap)
        geoplot(GT,ColorVariable="Power (dBm)",EdgeColor="k",FaceAlpha=0.5)
        colormap(cmap)
        clim([min(levels) max(levels)+10])
        h = colorbar:
        h.Label.String = "Power (dBm)";
        h.Ticks = levels;
        for k = 1:length(txsites)
            latt = txsites(k).Latitude;
            lont = txsites(k).Longitude;
            text(latt,lont,txsites(k).Name,Color="w")
        end
       title("Coverage Contour Map")
   % If you specify an output argument, return a geospatial table
   else
        varargout{1} = GT;
   end
end
```

The findNanDelimitedParts helper function finds the indices of the first and last elements of each NaN-separated part of the array x. The contourDataGrid helper function uses findNanDelimitedParts.

```
function [first,last] = findNanDelimitedParts(x)
% Find indices of the first and last elements of each part in x.
% x can contain runs of multiple NaNs, and x can start or end with
% one or more NaNs.

n = isnan(x(:));

firstOrPrecededByNaN = [true; n(1:end-1)];
  first = find(~n & firstOrPrecededByNaN);

lastOrFollowedByNaN = [n(2:end); true];
```

```
\label{last} \mbox{last0rFollowedByNaN);} \\ \mbox{end} \\
```

See Also

Functions

viewshed|contourf|coverage|geoplot|readBasemapImage

Objects

txsite | LongleyRice

Related Examples

- "Create Geospatial Tables" on page 2-18
- "Create Common Plots over Basemap Images" on page 6-19

Add Light Source to Terrain Map


Add a light source to a terrain map for a region around South Boulder Peak in Colorado.

First, import elevation data and a geographic postings reference object. To plot the data using geoshow, the raster data must be of type double or single. Therefore, specify the data type for the raster using the 'OutputType' name-value pair.

```
[Z,R] = readgeoraster('n39_w106_3arc_v2.dt1','OutputType','double');
```


Then, display the data as a surface. Apply a colormap appropriate for terrain data using the demcmap function.

```
usamap(R.LatitudeLimits,R.LongitudeLimits);
geoshow(Z,R,'DisplayType','surface')
demcmap(Z)
```




Set the vertical exaggeration using the daspectm function. Then, specify a light source in the top left corner of the map. Find the coordinates of the top left corner by querying the LatitudeLimits and LongitudeLimits properties of the reference object.

```
daspectm('m',20)
cornerlat = R.LatitudeLimits(2);
cornerlon = R.LongitudeLimits(1);
lightm(cornerlat,cornerlon)
```



Restore the luminance of the map by specifying the ambient, diffuse, and specular light strength.

```
ambient = 0.7;
diffuse = 1;
specular = 0.6;
material([ambient diffuse specular])
```



The DTED file used in this example is courtesy of the US Geological Survey.

See Also

daspectm|lightm

More About

• "Lighting Overview"

Surface Relief Shading

You can make dimensional monochrome shaded-relief maps with the surflm function, which is similar to the surfl function. The effect of surflm is similar to using lights, but the function models illumination itself (with one "light source" that you specify when you invoke it, but cannot reposition) by weighting surface normals rather than using light objects.


Shaded relief maps of this type are usually portrayed two-dimensionally rather than as perspective displays. The surflm function works with any projection except globe.

The surflm function accepts geolocated data grids only. Recall, however, that regular data grids are a subset of geolocated data grids, to which they can be converted using the <code>geographicGrid</code> function. The following example illustrates this procedure.

Create Monochrome Shaded Relief Map


Simulate a single light source in a figure using surflm. First, load elevation data and a geographic cells reference object for the Korean peninsula. Import coastline vector data using readgeotable. Create a map with appropriate latitude and longitude limits using worldmap.

```
load korea5c
latlim = korea5cR.LatitudeLimits;
lonlim = korea5cR.LongitudeLimits;
coastline = readgeotable("landareas.shp");
worldmap(latlim,lonlim)
Display the coastline data using geoshow.
geoshow(coastline,'FaceColor','none')
```




Transform the regular data grid to a geolocated data grid using the <code>geographicGrid</code> function. Then, generate a shaded relief map using <code>surflm</code>. By default, the lighting direction is 45° counterclockwise from the viewing direction. Therefore, the light source is in the southeast. Change the colormap to the monochromatic colormap 'copper'.

```
[klat,klon] = geographicGrid(korea5cR);
s = surflm(klat,klon,korea5c);
colormap('copper')
```




Clear the map. Then, display the shaded relief map with a different light source by specifying the azimuth as 135° and the elevation as 60° . The surface lightens and has a new character because it is lit closer to overhead and from a different direction.

```
clmo(s)
s = surflm(klat,klon,korea5c,[135 60]);
```



Shift the light to the northwest by specifying the azimuth as -135° . Lower the light to 40° above the horizon. A lower light source decreases the overall reflectance of the surface when viewed from above. Therefore, specify a 1-by-4 vector of reflectance constants that describe the relative contributions of ambient light, diffuse reflection, specular reflection, and the specular shine coefficient.

```
clmo(s);
ht = surflm(klat,klon,korea5c,[-135 30],[0.65 0.4 0.3 10]);
```



The mountain ridges that run from northeast to southwest are approximately perpendicular to the light source. Therefore, these parameters demonstrate appropriate lighting for the terrain.

The monochromatic coloration in this example does not differentiate land from water. For an example that differentiates land from water, see "Colored Surface Shaded Relief" on page 5-43.

See Also

Functions

surflm | geographicGrid

Related Examples

- "Add Light Source to Terrain Map" on page 5-35
- "Relief Mapping with Light Objects" on page 5-47

Colored Surface Shaded Relief

The functions meshlsrm and surflsrm display maps as shaded relief with surface coloring as well as light source shading. You can think of them as extensions to surflm that combine surface coloring and surface light shading. Use meshlsrm to display regular data grids and surflsrm to render geolocated data grids.

These two functions construct a new colormap and associated CData matrix that uses grayscales to lighten or darken a matrix component based on its calculated surface normal to a light source. While there are no analogous MATLAB display functions that work like this, you can obtain similar results using MATLAB light objects, as "Relief Mapping with Light Objects" on page 5-47 explains.

For further information, see the reference pages for surflsrm, meshlsrm, daspectm, and view.


Create Colored Shaded Relief Map

Display surface illumination over colored elevation data using surflsrm. First, load elevation data and a geographic cells reference object for the Korean peninsula. Georeference the regular data grid using geographicGrid.

```
load korea5c
[klat,klon] = geographicGrid(korea5cR);
```

Create a colormap appropriate for elevation data. Plot the colored shaded relief map by specifying a light source with an azimuth of -130° and an altitude of 50° . The surflsrm function transforms the colormap to shade relief according to the light source. Eliminate white space around the map using tightmap.


```
[cmap,clim] = demcmap(korea5c);
axesm('miller','MapLatLimit',[30 45],'MapLonLimit',[115 135])
surflsrm(klat,klon,korea5c,[-130 50],cmap,clim)
tightmap
```



You can achieve the same effect using meshlsrm, which operates on regular data grids.


The surface has more contrast than if it were not shaded. Lighten the surface uniformly by 25%.

brighten(0.25)



Display an oblique view of the surface. Hide the bounding box by setting the Box property, exaggerate terrain relief by a factor of 50 using daspectm, and set the view to an azimuth of -30° and an altitude of 30° .

```
set(gca,'Box','off')
daspectm('meters',50)
view(-30,30)
```



You can continue rotating the perspective using view or the **Rotate 3D** tool in the figure window. You can continue changing the vertical exaggeration using daspectm. To change the built-in lighting direction, you must generate a new view using surflsrm.

Relief Mapping with Light Objects

This example shows how to create a light object to mimic the map produced in "Colored Surface Shaded Relief" on page 5-43, which uses shaded relief computations rather than light objects.


The meshlsrm and surflsrm functions simulate lighting by modifying the colormap with bands of light and dark. The map matrix is then converted to indices for the new "shaded" colormap based on calculated surface normals. Using light objects allows for a wide range of lighting effects. The toolbox manages light objects with the lightm function, which depends upon the MATLAB light function. Lights are separate MATLAB graphic objects.

For more information, consult the reference pages for lightm, daspectm, material, lighting, and view, along with "Lighting, Transparency, and Shading".

Illuminate Color 3-D Relief Maps with Light Objects


Add a light source to a surface colored data grid using lightm. First, load elevation data and a geographic cells reference object for the Korean peninsula. Display the data without lighting effects using meshm. Apply a colormap appropriate for elevation data using demcmap. Eliminate extra white space around the map using tightmap.

```
load korea5c
axesm('miller','MapLatLimit',[30 45],'MapLonLimit',[115 135])
meshm(korea5c,korea5cR,size(korea5c),korea5c)
demcmap(korea5c)
tightmap
```




Place a light source at the northwest corner of the grid, one degree high, using lightm. The lightm function is similar to the MATLAB® function light, but accepts latitude and longitude inputs instead of x, y, and z. Note that the figure becomes darker.

lightm(45,115,1)




Exaggerate the vertical dimension to make any relief viewable in perspective. Note that the figure becomes darker still.

daspectm('meters',50)




Set the ambient (direct), diffuse (skylight), and specular (highlight) surface reflectivity characteristics, respectively.

material([0.7 0.9 0.8])




By default, the lighting is flat (plane facets). Change the light to use Gouraud shading (interpolated normal vectors at facet corners).

lighting Gouraud




Remove the edges of the bounding box. Change the view by specifying an azimuth of -30 $^{\circ}$ and an altitude of 30 $^{\circ}$.

```
ax = gca;
ax.Box = 'off';
view(-30,30)
```



If there is only one light in the current figure, you can remove it using clmo. clmo(handlem('light'))



Drape Data on Elevation Maps

Combine Elevation Maps with Other Kinds of Data

Lighting effects can provide important visual cues when elevation maps are combined with other kinds of data. The shading resulting from lighting a surface makes it possible to "drape" satellite data over a grid of elevations. It is common to use this kind of display to overlay georeferenced land cover images from Earth satellites such as LANDSAT and SPOT on topography from digital elevation models.

When the elevation and image data grids correspond pixel-for-pixel to the same geographic locations, you can build up such displays using the optional altitude arguments in the surface display functions. If they do not, you can interpolate one or both source grids to a common mesh.

Drape Data over Terrain with Different Gridding

If you want to combine elevation and attribute (color) data grids that cover the same region but are gridded differently, you must resample one matrix to be consistent with the other. That is, you can construct a geolocated grid version of the regular data grid values or construct a regular grid version of the geolocated data grid values.

It helps if at least one of the grids is a geolocated data grid, because their explicit horizontal coordinates allow them to be resampled using the <code>geointerp</code> function. These examples show how to drape data over terrain with different gridding.

Combine Dissimilar Grids by Converting Regular Grid to Geolocated Data Grid

This example shows how to combine an elevation data grid and an attribute (color) data grid that cover the same region but are gridded differently. The example drapes slope data from a regular data grid on top of elevation data from a geolocated data grid. The example uses the geolocated data grid as the source for surface elevations and transforms the regular data grid into slope values, which are then sampled to conform to the geolocated data grid (creating a set of slope values for the diamond-shaped grid) and color-coded for surface display. This approach works with any dissimilar grids, although the two data sets in this example actually have the same origin (the geolocated grid derives from the topo60c data set).

Load the geolocated data grid from the mapmtx file and the regular data grid from the topo60c file. The mapmtx file actually contains two regions but this example only uses the diamond-shaped portion, lt1, lg1, and map1, centered on the Middle East.

```
load mapmtx lt1 lg1 map1
load topo60c
```

Compute the surface aspect, slope, and gradients for topo60c. This example only uses the slopes in subsequent steps.

```
[aspect,slope,gradN,gradE] = gradientm(topo60c,topo60cR);
```

Use the geointerp function to interpolate slope values to the geolocated grid specified by lt1 and lg1. The output is a 50-by-50 grid of elevations matching the coverage of the map1 variable.


```
slope1 = geointerp(slope,topo60cR,lt1,lg1);
```

Set up a figure with a Miller projection and use surfm to display the slope data. Specify the z-values for the surface explicitly as the map1 data, which is terrain elevation. The map mainly depicts steep cliffs, which represent mountains (the Himalayas in the northeast), and continental shelves and trenches.

```
figure
axesm miller
surfm(lt1,lg1,slope1,map1)
```

The coloration depicts steepness of slope. Change the colormap to make the steepest slopes magenta, the gentler slopes dark blue, and the flat areas light blue:

colormap cool



Use view to get a southeast perspective of the surface from a low viewpoint. In 3-D, you can see the topography as well as the slope.


```
view(20,30)
daspectm('meter',200)
```

The default rendering uses faceted shading (no smooth interpolation). Make the surface shiny with Gouraud shading and specify lighting from the east (the default of camlight lights surfaces from over the right shoulder of the viewer).

```
material shiny
camlight
lighting Gouraud
```

Remove the white space and view the figure in perspective mode.

```
axis tight
ax = gca;
ax.Projection = 'perspective';
```



Drape Geolocated Grid on Regular Data Grid via Texture Mapping

This example shows how to create a new regular data grid that covers the region of the geolocated data grid, then embed the color data values into the new matrix. The new matrix might need to have somewhat lower resolution than the original, to ensure that every cell in the new map receives a value. The example combines dissimilar data grids by creating a new regular data grid that covers the region of the geolocated data grid's z-data. This approach has the advantage that more computational functions are available for regular data grids than for geolocated ones. Color and elevation grids do not have to be the same size. If the resolutions of the two data grids are different, you can create the surface as a three-dimensional elevation map and later apply the colors as a texture map. You do this by setting the surface CData property to contain the color matrix, and setting the surface face color to 'texturemap'.

Load elevation raster data and a geographic cells reference object from topo60c.mat. Get individual variables containing terrain data from mapmtx.mat.

```
load topo60c
load mapmtx lt1 lg1 map1
```

Identify the geographic limits of the geolocated grid that was loaded from mapmtx.

```
latlim(1) = 2*floor(min(lt1(:))/2);
lonlim(1) = 2*floor(min(lg1(:))/2);
latlim(2) = 2*ceil(max(lt1(:))/2);
lonlim(2) = 2*ceil(max(lg1(:))/2);
```

Crop the global elevation data to the rectangular region enclosing the smaller grid.

```
[topo1,topo1R] = geocrop(topo60c,topo60cR,latlim,lonlim);
```

Allocate a regular grid filled uniformly with -Inf, to receive texture data.

```
L1R = georefcells(latlim,lonlim,2,2);
L1 = zeros(L1R.RasterSize);
L1 = L1 - Inf;
```

Overwrite L1 using imbedm, converting it from a geolocated grid to a regular grid, in which the values come from the discrete Laplacian of the elevation grid map1.


```
L1 = imbedm(lt1,lg1,del2(map1),L1,L1R);
```

Set up an axesm-based map with the Miller projection and use meshm to display the cropped data. Render the figure as a 3-D view from a 20 degree azimuth and 30 degree altitude, and exaggerate the vertical dimension by a factor of 200. Both the surface relief and coloring represent topographic elevation.

```
figure
axesm miller
h = meshm(topo1,topo1R,size(topo1),topo1);
view(20,30)
daspectm('m',200)
```

Apply the L1 matrix as a texture map directly to the surface using the set function. The area not covered by the [lt1,lg1,map1] geolocated data grid appears dark blue because the corresponding elements of L1 were set to -Inf.

```
h.CData = L1;
h.FaceColor = 'texturemap';
material shiny
camlight
lighting gouraud
axis tight
```



See Also

Functions

geointerp|georefcells|imbedm

Related Examples

• "Drape Geoid Heights over Topography" on page 5-60

Drape Geoid Heights over Topography


Display geoid data draped over topographic relief. For this example, display the geoid data as a color attribute instead of a 3-D surface.

Load topographic raster data and a geographic cells reference object. Get geoid heights by calling the eqm96geoid function and specifying the reference object.

```
load topo60c
[N,R] = egm96geoid(topo60cR);
```


Create an axesm-based map using a Gall stereographic cylindrical projection (a perspective projection). Use meshm to display variations of the geoid in color, but specify topo60c as the final argument, to give each geoid grid cell the height (z value) of the corresponding topographic grid cell. Low geoid heights are shown as blue, high ones as yellow.

```
axesm gstereo;
meshm(N,R,size(N),topo60c)
```




For reference, plot the world coastlines in black, raise their elevation to 1000 meters (high enough to clear the surface in their vicinity), and expand the map to fill the frame.

```
load coastlines
plotm(coastlat,coastlon,'k')
zdatam(handlem('allline'),1000)
tightmap
```




Due to the vertical view and lack of lighting, the topographic relief is not visible, but it is part of the figure's surface data. Bring it out by exaggerating relief greatly, and then setting a view from the south-southeast.

daspectm('m',200); tightmap
view(20,35)




Remove the bounding box, shine a light on the surface (using the default position, offset to the right of the viewpoint), and render again with Gouraud shading.

```
ax = gca;
ax.Box = 'off';
camlight;
lighting Gouraud
```



Finally, set the perspective to converge slightly (the default perspective is orthographic). Notice that the geoid mirrors the topography of the major mountain chains such as the Andes, the Himalayas, and the Mid-Atlantic Ridge. You can also see that large areas of high or low geoid heights are not simply a result of topography.

```
ax.Projection = 'perspective';
```



Combine Dissimilar Grids by Converting Regular Grid to Geolocated Data Grid

This example shows how to combine an elevation data grid and an attribute (color) data grid that cover the same region but are gridded differently. The example drapes slope data from a regular data grid on top of elevation data from a geolocated data grid. The example uses the geolocated data grid as the source for surface elevations and transforms the regular data grid into slope values, which are then sampled to conform to the geolocated data grid (creating a set of slope values for the diamond-shaped grid) and color-coded for surface display. This approach works with any dissimilar grids, although the two data sets in this example actually have the same origin (the geolocated grid derives from the topo60c data set).

Load the geolocated data grid from the mapmtx file and the regular data grid from the topo60c file. The mapmtx file actually contains two regions but this example only uses the diamond-shaped portion, lt1, lg1, and map1, centered on the Middle East.

```
load mapmtx lt1 lg1 map1
load topo60c
```

Compute the surface aspect, slope, and gradients for topo60c. This example only uses the slopes in subsequent steps.

```
[aspect,slope,gradN,gradE] = gradientm(topo60c,topo60cR);
```

Use the geointerp function to interpolate slope values to the geolocated grid specified by lt1 and lg1. The output is a 50-by-50 grid of elevations matching the coverage of the map1 variable.


```
slope1 = geointerp(slope,topo60cR,lt1,lq1);
```

Set up a figure with a Miller projection and use surfm to display the slope data. Specify the z-values for the surface explicitly as the map1 data, which is terrain elevation. The map mainly depicts steep cliffs, which represent mountains (the Himalayas in the northeast), and continental shelves and trenches.

```
figure
axesm miller
surfm(lt1,lg1,slope1,map1)
```

The coloration depicts steepness of slope. Change the colormap to make the steepest slopes magenta, the gentler slopes dark blue, and the flat areas light blue:

```
colormap cool
```



Use view to get a southeast perspective of the surface from a low viewpoint. In 3-D, you can see the topography as well as the slope.


```
view(20,30)
daspectm('meter',200)
```

The default rendering uses faceted shading (no smooth interpolation). Make the surface shiny with Gouraud shading and specify lighting from the east (the default of camlight lights surfaces from over the right shoulder of the viewer).

```
material shiny
camlight
lighting Gouraud
```

Remove the white space and view the figure in perspective mode.

```
axis tight
ax = gca;
ax.Projection = 'perspective';
```



Access Basemaps and Terrain for Geographic Globe

Geographic globe objects created using the **geoglobe** function plot data over basemaps and terrain. You can access different basemap and terrain choices in different ways.

MathWorks offers a selection of basemaps, including two-tone, color terrain, and high-zoom-level displays. Six of the basemaps are tiled data sets created using Natural Earth. Five of the basemaps are high-zoom-level maps provided by Esri. For more information about basemap options, see the geobasemap function.

Use Installed Basemap

The "darkwater" basemap is installed with MATLAB. The other basemaps are not installed with MATLAB, but you can access them over an internet connection.

Download Basemaps

To work offline or to improve map responsiveness, you can download the basemaps created using Natural Earth onto your local system. The basemaps provided by Esri are not available for download.

Download basemaps using the Add-On Explorer.

- 1 On the MATLAB **Home** tab, in the **Environment** section, click **Add-Ons** > **Get Add-Ons**.
- In the Add-On Explorer, scroll to the **MathWorks Optional Features** section, and click **Show**All to find the basemap add-ons. You can also search for the basemap add-ons by name (listed in the following table) or click **Optional Features** in **Filter by Type**.
- **3** Select the basemap add-ons that you want to download.

Basemap Name	Basemap Data Package Name
'bluegreen'	MATLAB Basemap Data - bluegreen
'grayland'	MATLAB Basemap Data - grayland
'colorterrain'	MATLAB Basemap Data - colorterrain
'grayterrain'	MATLAB Basemap Data - grayterrain
'landcover'	MATLAB Basemap Data - landcover

Add Custom Basemaps

Add custom basemaps from a URL or an MBTiles file containing raster map tiles by using the addCustomBasemap function. MATLAB requires an active internet connection to add and use custom basemaps from a URL. MATLAB does not require internet access to add custom basemaps from an MBTiles file.

Access Terrain

By default, the geographic globe uses terrain data hosted by MathWorks and derived from the GMTED2010 model by the USGS and NGA. You need an active internet connection to access this terrain data, and you cannot download it.

To work offline or to improve terrain responsiveness, add custom terrain from DTED files using the addCustomTerrain function. You do not need an active internet connection to add or use custom terrain.

Alternatively, you can set the Terrain property of the geographic globe object to 'none'.

Specify Basemaps and Terrain

To specify a basemap for a geographic globe, you can either:

• Use the **geobasemap** function. Specify the geographic globe as the first argument.

```
uif = uifigure;
g = geoglobe(uif);
geobasemap(g,'streets')
```

• Set the Basemap property of the GeographicGlobe object. You can set this property by using a name-value pair or by using dot notation.

```
uif = uifigure;
g = geoglobe(uif, 'Basemap', 'streets');
g.Basemap = 'topographic';
```

To specify terrain for the geographic globe, set the Terrain property of the GeographicGlobe object. You can set this property by using a name-value pair or by using dot notation.

```
uif = uifigure;
g = geoglobe(uif, 'Terrain', 'none');
g.Terrain = 'gmted2010';
```

See Also

geoglobe | geobasemap | addCustomTerrain | addCustomBasemap

More About

- "Use Basemaps in Offline Environments" on page 6-32
- "System Requirements for Graphics"
- "Resolving Low-Level Graphics Issues"

Create Interactive Basemap Picker


Interactively change the basemap of a geographic globe by adding a drop-down menu to the figure.

First, create a program file called basemapPicker.m. Within the program file:

- Create a geographic globe in a figure created using the uifigure function.
- Specify a position for the menu. In this example, the values of x, y, w, and h position the menu in the upper-right corner of the figure window.
- Specify the basemaps to include in the menu.
- Create the menu. Use a ValueChangedFcn callback that executes when you make a selection from the menu. The callback changes the basemap using the geobasemap function.
- Write custom code to reposition the menu when you change the size of the figure. To do this, disable automatic resizing of the menu. Then, create custom behavior by defining a SizeChangedFcn callback. The repositionDropdown function repositions the menu, so that it stays in the upper-right corner of the figure.

```
function basemapPicker
    uif = uifiqure;
    gl = geoglobe(uif);
    x = 0.8;
    y = 0.9;
    w = 0.2;
    h = 0.1;
    uifW = uif.Position(3);
    uifH = uif.Position(4);
    pos = [x*uifW y*uifH w*uifW h*uifH];
    basemaps = ["satellite" "streets" "streets-light" "streets-dark" ...
                "landcover" "darkwater" "grayland" "bluegreen" ...
                "grayterrain" "colorterrain"];
    dd = uidropdown(uif, 'Position', pos, 'Items', basemaps);
    dd.ValueChangedFcn = @(src,eventdata)geobasemap(gl,src.Value);
    uif.AutoResizeChildren = 'off';
    uif.SizeChangedFcn = @(src,eventdata)repositionDropdown(dd,x,y,w,h);
end
function repositionDropdown(dd,x,y,w,h)
    fig = dd.Parent;
    uifW = fig.Position(3);
    uifH = fig.Position(4);
    dd.Position = [x*uifW y*uifH w*uifW h*uifH];
end
```

Run the program file. Change the basemap to 'colorterrain' using the drop-down menu.



See Also

geoglobe|geobasemap|uidropdown

More About

• "Create Callbacks for Graphics Objects"

Visualize Aircraft Line-of-Sight over Terrain

This example shows how to compute and visualize the line-of-sight visibility of an aircraft from a ground location over terrain. First, import terrain data for a region and apply it to a 3-D geographic globe. Then, perform point-to-point visibility analysis from a ground location to a simulated flight path, and display the results on a 3-D geographic globe. Finally, perform point-to-area visibility analysis from the ground location corresponding to aircraft flying at constant altitude, and display the results on a 2-D geographic axes.

Use line-of-sight analysis for ground-to-air scenarios where unobstructed visibility is important, such as for radar surveillance, communications, and UAV path planning. This example applies the analysis to radar surveillance for an airport.

Import Terrain Data

Specify a DTED-format terrain file to use for data analysis and 3-D visualization. The terrain file was downloaded from the "SRTM Void Filled" data set available from the United States Geological Survey (USGS).

```
dtedfile = "n39_w106_3arc_v2.dt1";
attribution = "SRTM 3 arc-second resolution. Data available from the U.S. Geological Survey.";
```

Import DTED file data into the workspace as an array and a geographic raster reference object, specifying the return type as double so that the data works with all analysis functions.

```
[Zterrain,Rterrain] = readgeoraster(dtedfile, "OutputType", "double");
```

View the geographic limits and sample resolution of the terrain data by accessing properties of the geographic raster reference object. The limits for the file correspond to the region around Boulder, Colorado, US, and the resolution corresponds to the DTED level-1 format, which has sample resolution of 3 arc seconds, or about 90 meters.

```
latlim = Rterrain.LatitudeLimits;
lonlim = Rterrain.LongitudeLimits;
latspc = Rterrain.SampleSpacingInLatitude;
lonspc = Rterrain.SampleSpacingInLongitude;
disp("Latitude limits of terrain: " + mat2str(latlim) + newline + ...
    "Longitude limits of terrain: " + mat2str(lonlim) + newline + ...
    "Terrain resolution in latitude: " + latspc*3600 + " arc seconds" + newline + ...
    "Terrain resolution in longitude: " + lonspc*3600 + " arc seconds")

Latitude limits of terrain: [39 40]
Longitude limits of terrain: [-106 -105]
Terrain resolution in latitude: 3 arc seconds
Terrain resolution in longitude: 3 arc seconds
```

Visualize Aircraft Trajectory Line-of-Sight on a 3-D Map

Create Geographic Globe with Custom Terrain

Add custom data with the DTED file for use with 3-D visualization.

```
addCustomTerrain("southboulder",dtedfile,"Attribution",attribution)
```

Specify the custom terrain with a new geographic globe.

```
fig = uifigure;
g = geoglobe(fig, "Terrain", "southboulder");
```


View Radar Ground Location

Define a radar ground location at Rocky Mountain Metropolitan Airport. The radar is mounted on a tower 10 meters above the ground. The radar altitude is the sum of the ground elevation and the radar tower height, referenced to mean sea level.

```
rdrlat = 39.913756;
rdrlon = -105.118062;
rdrtowerht = 10;
rdralt = 1717 + rdrtowerht;
```

Plot the radar location on the geographic globe.

```
geoplot3(g,rdrlat,rdrlon,rdralt,"co", ...
    "LineWidth",6, ...
    "MarkerSize",1)
```



Simulate Aircraft Trajectory

Simulate the trajectory of an aircraft circling over the mountains.

Define the center location of a circling aircraft.

```
tlat0 = 39.80384;
tlon0 = -105.49916;
tht0 = 3000;
```

Define trajectory waypoints for the aircraft using east-north-up (ENU) Cartesian coordinates. Specify a curve with a radius of 5 km (5000 m) and a vertical offset of 1 km (1000 m) over 1.5 revolutions. Then, convert the ENU coordinates to geodetic coordinates that are referenced to the WGS84 ellipsoid.

```
azs = 1:540;
r = 5000;
[X,Y] = pol2cart(deg2rad(azs),r);
Z = linspace(0,1000,numel(azs));
wgs84 = wgs84Ellipsoid;
[tlat,tlon,tht] = enu2geodetic(X,Y,Z,tlat0,tlon0,tht0,wgs84);
```

View Aircraft Trajectory over Terrain


Plot the aircraft trajectory on the geographic globe. The default view, or camera position, is overhead and oriented down.

```
hold(g,"on")
traj = geoplot3(g,tlat,tlon,tht,"y", ...
    "HeightReference","ellipsoid", ...
    "LineWidth",3);
```



View the 3-D terrain and radar location from a distance by changing the camera position and rotation angles.

campos(g,39.77114,-105.62662,6670)
camheading(g,70)
campitch(g,-12)



Compute Line-of-Sight Visibility with Aircraft Trajectory

Compute line-of-sight visibility with the los2 function and the DTED data.

The los2 function supports either orthometric height (height above mean sea level) or height above ground level. Convert the aircraft trajectory heights from ellipsoidal height to orthometric height. Then, compute the line-of-sight from the airport radar location to each aircraft trajectory waypoint and convert the results to a logical array.


```
numwaypts = numel(tlat);
isvis = zeros(1,numwaypts);
talt = tht - egm96geoid(tlat,tlon);
for k = 1:numwaypts
    isvis(k) = los2(Zterrain,Rterrain,rdrlat,rdrlon,tlat(k),tlon(k),rdralt,talt(k),"MSL","MSL");
end
isvis = logical(isvis);
```

Note that los2 calculates line-of-sight visibility assuming the data is referenced to a spherical Earth, whereas the data is actually referenced to the WGS84 ellipsoid, and as a result there may be minor discrepancies. The line-of-sight calculation also corresponds to optical line-of-sight and does not account for refraction through the atmosphere.

Visualize Line-of-Sight Visibility over Terrain

Plot the line-of-sight visibility. Use green markers where the aircraft is visible from the airport and magenta markers where it is not visible.

```
delete(traj)
geoplot3(g,tlat(isvis),tlon(isvis),tht(isvis),"og", ...
    "HeightReference","ellipsoid", ...
    "LineWidth",2, ...
    "MarkerSize",1)
geoplot3(g,tlat(~isvis),tlon(~isvis),tht(~isvis),"om", ...
    "HeightReference","ellipsoid", ...
    "LineWidth",2, ...
    "MarkerSize",1)
```



View the line-of-sight plot from the perspective of the airport. Get the geodetic coordinates of the position that is 900 meters east, 200 meters north, and 100 meters up from the radar location. Then, set the camera position and rotation angles. The green markers appear in view, but the magenta markers are either completely or partially obstructed by terrain.

```
rdrht = rdralt + egm96geoid(rdrlat,rdrlon);
[camlat,camlon,camht] = enu2geodetic(900,200,100,rdrlat,rdrlon,rdrht,wgs84);
campos(g,camlat,camlon,camht)
camheading(g,-110)
campitch(g,0)
```



Visualize Aircraft Line-of-Sight Visibility Contours on a 2-D Map

The previous sections performed point-to-point line-of-sight analysis and visualization from a radar location to an aircraft trajectory. Now perform point-to-area line-of-sight analysis and visualization from the same radar location over the terrain region. The visualization displays the edge of visibility for an aircraft flying at constant altitude.

Plot Radar Location and Terrain Limits on a 2-D Map

Plot the radar location in a new figure with a topographic 2-D map.


```
figure
geoplot(rdrlat,rdrlon,"co", ...
    "LineWidth",6, ...
    "MarkerSize",3, ...
    "DisplayName","Radar location")
geobasemap topographic
gx = gca;
gx.InnerPosition = gx.OuterPosition;

Display the limits of the custom terrain as a rectangle on the map.
latmin = latlim(1);
latmax = latlim(2);
lonmin = lonlim(1);
```

```
lonmax = lonlim(2);
hold on
geoplot([latmin latmin latmax latmax latmin],[lonmin lonmax lonmax lonmin lonmin], ...
    "LineWidth",1, ...
    "Color","k", ...
    "DisplayName","Terrain limits")
```

Display a legend in the northwest corner.

legend("Location", "northwest")




Plot Visibility Contours for Aircraft Flying at Constant Altitude

Specify three altitudes above mean sea level for the aircraft. For each altitude:

- Compute the viewshed using the radar location as the observer. The viewshed defines the area that has line-of-sight visibility.
- Find the edge of aircraft visibility by computing contours from the viewshed data.
- · Remove small contour segments.
- Plot the contours on the geographic axes.

```
tgtalts = [3000 4000 5000];
minVertices = 10;
cfig = figure("Visible","off"); % Suppress contour plot using invisible figure
cax = axes("Parent",cfig);
```

```
for tgtalt = tgtalts
   vis = viewshed(Zterrain,Rterrain,rdrlat,rdrlon,rdralt,tgtalt,"MSL","MSL");
   C = contourm(vis,Rterrain,"LevelList",1,"Parent",cax);
   clat = C(2,:);
   clon = C(1,:);
    clats = [];
   clons = [];
    k = 1;
   while k < size(C,2)</pre>
        numVertices = clat(k);
        if numVertices > minVertices % Do not plot small segments
            clats = [clats clat(k+1:k+numVertices) NaN]; %#ok<AGROW>
            clons = [clons clon(k+1:k+numVertices) NaN]; %#ok<AGROW>
        end
        k = k + numVertices + 1;
   end
   geoplot(gx,clats,clons,"LineWidth",2, ...
        "DisplayName", "Aircraft: " + string(tgtalt) + " m");
end
```



The contours appear primarily to the west of the radar location over the mountains. The contours do not appear in other directions because visibility is not constrained by the terrain in those directions within the terrain data limits.

If the radar is constrained by line-of-sight visibility, then the contours correspond to radar coverage regions for varying altitude, where the nearest contour to the radar corresponds to radar coverage for an aircraft flying at 3000 meters and the furthest contour corresponds to radar coverage for an aircraft flying at 5000 meters.

As with los2, the viewshed function calculates line-of-sight visibility assuming the data is referenced to a spherical Earth, whereas the data is actually referenced to the WGS84 ellipsoid, and as a result there may be minor discrepancies. The line-of-sight calculation also corresponds to optical line-of-sight and does not account for refraction through the atmosphere.

Clean Up

Clean up by closing the geographic globe and removing the imported terrain data.

```
if isvalid(fig)
    close(fig)
end
removeCustomTerrain("southboulder")
```

See Also

Functions

addCustomTerrain|geoplot3|geoglobe|los2|campos|readgeoraster

Objects

GeographicPostingsReference

More About

- "Find Ellipsoidal Height from Orthometric Height" on page 3-50
- "Find Geospatial Raster Data" on page 2-79

Visualize UAV Flight Path on 2-D and 3-D Maps

This example visualizes a simulated unmanned aerial vehicle (UAV) flight from the Mauna Loa Baseline Observatory to the top of the Mauna Loa Volcano in Hawaii. First, display the track on geographic axes and a geographic globe. Then, synchronize the view and visualize the flight path by using camera navigation functions. Finally, view the top of the Mauna Loa volcano as a panorama.

Visualize Region of Interest in 2-D

The use of UAVs to track characteristics of changing topology, gasses, and ash clouds around volcanos is becoming an important area of research for scientists [1]. A UAV can travel in regions that are hazardous for a volcanologist. Simulating the flight path of the UAV prior to sending it out on a mission can assist with understanding the topology and terrain. To gain an overview and 2-D perspective of the region, view the locations of the Mauna Loa Baseline Observatory and the Mauna Loa Volcano in a geographic axes.

Get Coordinates of Mauna Loa Baseline Observatory

Specify the coordinates of the Mauna Loa Baseline Observatory [2]. The height of the observatory is in meters above mean sea level (MSL).

```
obslat = 19.5362;
obslon = -155.5763;
obsH = 3397.00;
```

Get Coordinates of Mauna Loa Volcano


Specify the coordinates of the top of Mauna Loa [3]. The height of the volcano is orthometric and is in meters.

```
mllat = 19.475;
mllon = -155.608;
mlH = 4169;
```

View Mauna Loa Baseline Observatory and Mauna Loa Volcano in 2-D

For a 2-D perspective of the region, use **geoaxes** and **geoplot** to plot the location of the observatory and the top of the volcano.

```
figure
geoaxes("Basemap","satellite","ZoomLevel",12)
hold on
geoplot(obslat,obslon,"ow","MarkerSize",10,"MarkerFaceColor","magenta", ...
    "DisplayName","Mauna Loa Observatory")
geoplot(mllat,mllon,"ow","MarkerSize",10,"MarkerFaceColor","blue", ...
    "DisplayName","Mauna Loa Volcano")
legend
```




Synchronize View of Mauna Loa Baseline Observatory in 2-D and 3-D


Use the geographic axes to view the observatory in 2-D and the geographic globe to view the observatory in 3-D.

Create Geographic Axes and Geographic Globe in Same Figure

Set up a 2-D and 3-D map display by creating geographic axes and a geographic globe in the same UI figure. To view more of the 2-D map, set the InnerPosition of the geographic axes to its OuterPosition. To view both map displays with the same basemap, set the basemap of the geographic axes to "satellite".

```
figpos = [1000 500 800 400];
uif = uifigure("Position",figpos);
ug = uigridlayout(uif,[1,2]);
p1 = uipanel(ug);
p2 = uipanel(ug);
gx = geoaxes(p1,"Basemap","satellite");
gg = geoglobe(p2);
gx.InnerPosition = gx.OuterPosition;
gg.Position = [0 0 1 1];
```





View Observatory in 2-D

View the observatory from 200 meters above the terrain. Control the view of the geographic axes by changing its map center and zoom level. You can synchronize the view of the geographic axes with the view of the geographic globe by converting the camera height of the globe to a zoom level for the axes. Calculate an approximate zoom level from terrain height by using the heightToZoomLevel local function.

```
heightAboveTerrain = 200;
gx.MapCenter = [obslat, obslon];
zoomLevel = heightToZoomLevel(heightAboveTerrain, obslat);
gx.ZoomLevel = zoomLevel;
```

View Observatory in 3-D

Control the view of the geographic globe by changing the position of the camera. The campos function requires you to specify ellipsoidal height (relative to the WGS84 ellipsoid) instead of orthometric height (relative to mean sea level). Convert the height of the observatory to ellipsoidal height. All heights are in meters.

```
N = egm96geoid(obslat, obslon);
obsh = obsH + N;
ellipsoidalHeight = obsh + heightAboveTerrain;
campos(gg,obslat,obslon,ellipsoidalHeight)
drawnow
```





Import Flight Track Data and Calculate Heading and 3-D Distance

Import the simulated flight track from the Mauna Loa Baseline Observatory to the top of the Mauna Loa volcano. The file contains the latitudes, longitudes, and altitudes of the UAV path, referenced to mean sea level.

```
T = readgeotable("sample_uavtrack.gpx","Layer","track_points");
tlat = T.Shape.Latitude';
tlon = T.Shape.Longitude';
talt = T.Elevation';
```

Calculate Flight Headings

Calculate the UAV heading at each track point using the azimuth function.

```
wgs84 = wgs84Ellipsoid;
theading = azimuth(tlat(1:end-1),tlon(1:end-1),tlat(2:end),tlon(2:end),wgs84);
theading = [theading(1);theading(:)];
```

Calculate 3-D Distances

Calculate the cumulative distance for the UAV flight track. The distance function does not take into account changes in elevation or altitude. In order to calculate the distance the UAV moves from point to point in 3-D, you need to work in geocentric Cartesian coordinates (X, Y, Z). Compute the point-to-point offset components (in meters) using the ecefOffset function. The altitude data of the UAV flight is referenced to the mean sea level. To use the ecefOffset function, the heights must be referenced to the ellipsoid. Convert the orthometric heights of the flight track to ellipsoidal height (relative to the WGS84 ellipsoid). All heights are in meters.

```
N = egm96geoid(tlat,tlon);
h = talt + N;
```

Compute distance offsets.

```
lat1 = tlat(1:end-1);
lat2 = tlat(2:end);
lon1 = tlon(1:end-1);
lon2 = tlon(2:end);
h1 = h(1:end-1);
h2 = h(2:end);
[dx,dy,dz] = ecefOffset(wgs84,lat1,lon1,h1,lat2,lon2,h2);
```

Calculate the Euclidean distance between each pair of adjacent points using the hypot function. The distance is in meters.

```
distanceIncrementIn3D = hypot(hypot(dx, dy), dz);
```

Compute cumulative distance in 3-D and the total distance in meters.

```
cumulativeDistanceIn3D = cumsum(distanceIncrementIn3D);
totalDistanceIn3D = sum(distanceIncrementIn3D);
fprintf("Total UAV track distance is %f meters.\n",totalDistanceIn3D)
Total UAV track distance is 8931.072120 meters.
```

Assign a variable for the cumulative distance to be used for plotting the animation.

```
tdist = [0 cumulativeDistanceIn3D];
```

Plot Flight Line from Mauna Loa Baseline Observatory to top of Mauna Loa Volcano


Plot the simulated flight line from the Mauna Loa Baseline Observatory to the top of the Mauna Loa volcano.

Plot the flight line. By default, the geographic globe places the line at the center of the display. The view of the geographic axes will not change because you have previously set the MapCenter and ZoomLevel.

```
geoplot3(gg,tlat,tlon,talt,"c","LineWidth",2,"HeightReference","geoid")
ptrack = geoplot(gx,tlat,tlon,"c","LineWidth",2);
```

Set the map center and zoom level to be consistent with the 3-D view by converting the camera height for the globe to the zoom level for the axes.

```
[clat,clon,cheight] = campos(gg);
gx.MapCenter = [clat,clon];
gx.ZoomLevel = heightToZoomLevel(cheight, clat);
drawnow
```





Set Initial View from Mauna Loa Baseline Observatory to Top of Mauna Loa Volcano

View the flight line from the start position by setting the camera position to the first coordinate of the track. For a better perspective, set the camera height to 75 meters about the height of the track. View straight down to the observatory by setting the camera pitch to -90. View the track by setting the heading to the third element of the calculated heading array since the first two points of the track are the same location and the calculated heading for those locations is 0.

```
campos(gg,tlat(1),tlon(1))
camheight(gg,talt(1) + 75)
campitch(gg,-90)
camheading(gg,theading(3))
```

Show the location of the UAV in the 2-D map, and the start and end locations of the flight track with markers. Create a legend for the UAV track and markers.

```
hold(gx,"on")
marker = geoplot(gx,tlat(1),tlon(1),"ow","MarkerSize",10,"MarkerFaceColor","k");
mstart = geoplot(gx,tlat(1),tlon(1),"ow","MarkerSize",10,"MarkerFaceColor","magenta");
mend = geoplot(gx,tlat(end),tlon(end),"ow","MarkerSize",10,"MarkerFaceColor","blue");

marker.DisplayName = "Current Location";
mstart.DisplayName = "Start Location";
mend.DisplayName = "End Location";
ptrack.DisplayName = "UAV Track";
legend(gx)
```

View the topology of the region by changing the basemap.

```
gx.Basemap = "topographic";
```

View the coordinate location, altitude, and heading of the UAV by using a custom data tip that corresponds with the location of the UAV. Include the distance from the observatory.

```
dt = datatip(ptrack, "DataIndex",1, "Location", "southeast");
dtrow = dataTipTextRow("Distance",tdist);
dtrow(end+1) = dataTipTextRow("Altitude",talt);
dtrow(end+1) = dataTipTextRow("Heading",theading);
ptrack.DataTipTemplate.DataTipRows(end+1:end+3) = dtrow;
```



Fly from Mauna Loa Baseline Observatory to Top of Mauna Loa Volcano

Animate a flight from the Mauna Loa Baseline Observatory to the top of the Mauna Loa volcano. View the location of the UAV on the 2-D map by animating a marker and data tip. Animate the 3-D flight by setting the camera position. For a better view of the UAV track, set the camera height to 100 meters above the flight track. Update the camera pitch value for a better view of the flight track as the UAV navigates to the top of the volcano. To view the current location, altitude, and heading of the UAV, update the data tip with the current index.

```
pitch = -2.7689;
campitch(gg,pitch)

for k = 2:(length(tlat)-1)
    campos(gg,tlat(k),tlon(k))
    camheight(gg,talt(k)+100)
    camheading(gg,theading(k))

    set(marker, "LatitudeData",tlat(k), "LongitudeData",tlon(k));
    dt.DataIndex = k;

    drawnow
    pause(.25)
end

campos(gg,tlat(end),tlon(end),talt(end)+100)
dt.DataIndex = length(tlat);
```



View a 360-Degree Panorama from Top of Mauna Loa Volcano

View a 360-degree panorama from the top of Mauna Loa by rotating the camera heading 360 degrees. Rotate clockwise with a step size of 5-degrees and start at the next 5 degree step. Update the heading data tip.

```
initialHeading = camheading(gg);
increment = 5;
initialHeading = initialHeading + (increment - mod(initialHeading,increment));
filename = 'panoramic.gif';
for degree = initialHeading:increment:initialHeading+360
    heading = mod(degree,360);
    ptrack.DataTipTemplate.DataTipRows(end).Value(dt.DataIndex) = heading;
    camheading(gg,heading);
    drawnow
end
```



Local Functions

Convert Height (in meters above WGS84 ellipsoid) to Zoom Level

```
function zoomLevel = heightToZoomLevel(height, lat)
   earthCircumference = 2 * pi * 6378137;
   zoomLevel = log2((earthCircumference *cosd(lat)) / height) + 1;
   zoomLevel = max(0, zoomLevel);
   zoomLevel = min(19, zoomLevel);
end
```

References

- [1] Williams, Sarah C. P. "Studying Volcanic Eruptions with Aerial Drones." *Proceedings of the National Academy of Sciences of the United States of America* 110, no. 27 (July 2, 2013): 10881. https://doi.org/10.1073/pnas.1309922110.
- [2] NOAA. "Mauna Loa Baseline Observatory." Global Monitoring Laboratory. Accessed June 16, 2020. https://gml.noaa.gov/obop/mlo/.
- [3] USGS. "Mauna Loa." Hawaiian Volcano Observatory. Accessed June 16, 2020. https://www.usgs.gov/volcanoes/mauna-loa.

See Also

Functions

azimuth | campos | camroll | camheading | campitch | egm96geoid

Objects

GeographicGlobe

Properties

GeographicAxes Properties

More About

• "Find Ellipsoidal Height from Orthometric Height" on page 3-50

Customizing and Printing Maps

- "Inset Maps" on page 6-2
- "Thematic Maps" on page 6-4
- "Create Choropleth Map from Table Data" on page 6-7
- "Create Classification Map from Table Data" on page 6-11
- "Create Choropleth Map of Population Density" on page 6-15
- "Scale Maps for Printing" on page 6-18
- "Create Common Plots over Basemap Images" on page 6-19
- "Change Projection of Basemap Image" on page 6-27
- "Use Basemaps in Offline Environments" on page 6-32
- "Display Data over Basemaps When Internet Access Is Intermittent" on page 6-42

Inset Maps

An inset map is a smaller map displayed inside a larger map. You can use an inset map to create geographic context for the larger map. For this example, create a map of Massachusetts and include an inset map of the northeastern United States.

Read USA state boundaries from a shapefile. Indicate that file contains latitude and longitude coordinates by specifying the UseGeoCoords name-value argument.


```
states = shaperead('usastatehi.shp','UseGeoCoords',true);
```

Extract the state boundaries of Massachusetts and find their latitude and longitude limits.

```
ma = states(strcmp({states.Name},'Massachusetts'));
latlim = [min(ma.Lat) max(ma.Lat)];
lonlim = [min(ma.Lon) max(ma.Lon)];
```

Create a map using the latitude and longitude coordinates. Set the face frame color of the map to light blue. Display the USA boundaries as light-brown polygons and the Massachusetts boundaries as green polygons.


```
figure
h1 = usamap(latlim,lonlim);
setm(h1,'FFaceColor','#B7E9F7')
geoshow(states,'FaceColor','#EFE6DC')
geoshow(ma,'FaceColor','#90EE90')
```



73.5°W 73.0°W 72.5°W 72.0°W 71.5°W 71.0°W 70.5°W 70.0°W

Create an inset map. To do this, first create axes in the lower-left of the map frame. Place a map with latitude and longitude limits that contain Pennsylvania and Maine inside the axes, remove the parallel and meridian labels, and remove the grid lines. Then, display the USA boundaries as gray polygons and the Massachusetts boundaries as green polygons.

```
h2 = axes('Position',[0.15 0.25 0.2 0.2]);
usamap({'PA','ME'})
setm(h2,'FFaceColor','w')
plabel off
mlabel off
gridm off
geoshow(states,'FaceColor','#EDEDED')
geoshow(ma,'FaceColor','#90EE90')
```



73.5°W 73.0°W 72.5°W 72.0°W 71.5°W 71.0°W 70.5°W 70.0°W

See Also

Functions

usamap | geoshow | shaperead

Related Examples

• "Create Map Displays with Geographic Data" on page 4-66

Thematic Maps

Most published and online maps fall into four categories:

- · Navigation maps, including topographic maps and nautical and aeronautical charts
- Geophysical maps, that show the structure and dynamics of earth, oceans and atmosphere
- · Location maps, that depict the locations and names of physical features
- Thematic maps, that portray attribute data about locations and features

Although online maps often combine these categories in new and unexpected ways, published maps and atlases tend to respect them.

Thematic maps tend to be more highly stylized than other types of maps and frequently omit locational information such as place names, physical features, coordinate grids, and map scales. This is because rather than showing physical features on the ground, such as shorelines, roads, settlements, topography, and vegetation, a thematic map displays quantified facts (a "theme"), such as statistics for a region or sets of regions. Examples include the locations of traffic accidents in a city, or election results by state. Thematic maps have a wide vocabulary of cartographic symbols, such as point symbols, dot distributions, "quiver" vectors, isolines, colored zones, raised prisms, and continuous 3-D surfaces.


Choropleth and Classification Maps

Choropleth and classification maps use colors or patterns to represent attributes associated with certain geographic regions.

- Choropleth maps indicate the values of numeric attributes within spatial regions by using colors along a gradient. Choropleth maps are commonly used to illustrate population density within specified regions. For examples of how to create choropleth maps, see "Create Choropleth Map of Population Density" on page 6-15 and "Create Choropleth Map from Table Data" on page 6-7.
- Classification maps indicate the values of classified or categorical attributes within spatial regions by using discrete colors. Classification maps are commonly used to illustrate climate classes, land cover classes, and binned population density within specified regions. For an example of how to create a classification map, see "Create Classification Map from Table Data" on page 6-11.

Stem Maps


Stem plots are 3-D geographic bar graphs portraying numeric attributes at point locations, usually on vector base maps. Below is an example of a stem plot over a map of the continental United States. The bars could represent anything from selected city populations to the number of units of a product purchased at each location.



You can create stem plots over axesm-based maps by using the stem3m function.

Contour Maps

Contour and quiver plots can be useful in analyzing matrix data. This image shows contour elevation lines and quiver plots over a topographical map of the Gulf of Mexico. The quiver plots illustrate the gradient of the topographical matrix.



Create contour plots by using the contourm, contour3m, or contourfm function. Create 2-D or 3-D quiver plots over axesm-based maps by using the quiverm or quiver3m function.

Scatter Maps

Similar to the MATLAB scatter function, the scatterm function plots symbols on axesm-based maps at specified point locations. If the symbols are small and inconspicuous and do not vary in size, the result is a *dot-distribution map*. If the symbols vary in size and/or shape according to a vector of attribute values, the result is a *proportional symbol map*.

See Also

Functions geoplot

Related Examples

"Create Common Plots over Basemap Images" on page 6-19

Create Choropleth Map from Table Data

This example shows how to create a choropleth map from spatial and attribute data contained in tables. A *choropleth map* indicates the values of numeric attributes within spatial regions by using colors along a gradient. Choropleth maps are commonly used to illustrate population density within specified regions.

To create a classification map, where discrete colors indicate the values of classified or categorical attributes, see "Create Classification Map from Table Data" on page 6-11.

Read Data into Tables

Read a comma-separated text file into a table. The file contains farmland statistics for each US state and the District of Columbia, based on the National Agricultural Statistics Service (NASS) Farms and Land in Farms 2019 Summary. For more information about the statistics, see [1] on page 6-10. Display the first row of the table.

To create a map from the table, you also need spatial information. Read a shapefile containing polygon shapes for each of the US states and the District of Columbia into a geospatial table. A *geospatial table* has a Shape variable containing shape information for each row. Display the first row of the geospatial table.

The Shape variable of the table contains geopolyshape objects, which are polygons in geographic coordinates. Display the properties of the geopolyshape object in the first row.

```
states.Shape(1)
ans =
   geopolyshape with properties:

        NumRegions: 1
        NumHoles: 0
        Geometry: "polygon"
   CoordinateSystemType: "geographic"
        GeographicCRS: [1×1 geocrs]
```

Join Tables

The table of farmland statistics identifies the District of Columbia as Washington DC, which does not match the corresponding row of the table of polygon shapes. Change the name in the table of farmland statistics so that it matches the name in the table of polygon shapes.

```
dcRow = farms.StateName == "Washington DC";
farms.StateName(dcRow) = "District of Columbia";
```

"Alabama"

Join the tables, using the state name variables Name and StateName as the key variables. Display the first row of the joined table.

-86.921

87.6

"Alabama"

38800

For more information about how to combine vector data using table joins, see "Combine Vector Data Using Table Joins" on page 2-23.

32.283

Create Choropleth Map

geopolyshape

Create a choropleth map that shows the average farm size for each state in the conterminous US.


```
figure
rows = statesFarms.Name ~= "Hawaii" & statesFarms.Name ~= "Alaska";
statesFarmsConus = statesFarms(rows,:);
geoplot(statesFarmsConus,ColorVariable="AverageFarmSize");
```

Change the basemap. Add a title and a labeled colorbar.

```
geobasemap darkwater
title("Average Farm Size Per US State in 2019")
cb = colorbar;
cb.Label.String = "Size in Acres";
```

Change the colormap so that, as the average farm sizes increase, the colors of the states transition from yellow to green.


```
cmap = flip(summer);
colormap(cmap)
```



Export Map

Export the map to a PNG file.

gx = gca; exportgraphics(gx,"AverageFarmSizeForUS.png")



References

[1] National Agricultural Statistics Service. "Number of Farms, Land in Farms, and Average Farm Size — States and United States: 2018–2019." *In Farms and Land in Farms 2019 Summary*, 6. USDA, February 2020. https://www.nass.usda.gov/Publications/Todays_Reports/reports/fnlo0220.pdf.

See Also

Functions

readgeotable | geoplot | colormap

Properties

Point Properties | Line Properties | Polygon Properties

Related Examples

- "Create Geospatial Tables" on page 2-18
- "Create Classification Map from Table Data" on page 6-11

Create Classification Map from Table Data

The example shows how to create a classification map from spatial and attribute data contained in tables. A *classification map* indicates the values of classified or categorical attributes within spatial regions by using discrete colors. Classification maps are commonly used to illustrate climate classes, land cover classes, and binned population density within specified regions.

To create a choropleth map, where colors along a gradient indicate the values of numeric attributes, see "Create Choropleth Map from Table Data" on page 6-7.

Read Data into Tables

Read a comma-separated text file into a table. The file contains farmland statistics for each US state and the District of Columbia, based on the National Agricultural Statistics Service (NASS) Farms and Land in Farms 2019 Summary. For more information about the statistics, see [1] on page 6-14. Display the first row of the table.

To create a map from the table, you also need spatial information. Read a shapefile containing polygon shapes for each of the US states and the District of Columbia into a geospatial table. A *geospatial table* has a Shape variable containing shape information for each row. Display the first row of the geospatial table.

The Shape variable of the table contains geopolyshape objects, which are polygons in geographic coordinates. Display the properties of the geopolyshape object in the first row.

Join Tables

The table of farmland statistics identifies the District of Columbia as Washington DC, which does not match the corresponding row of the table of polygon shapes. Change the name in the table of farmland statistics so that it matches the name in the table of polygon shapes.

```
dcRow = farms.StateName == "Washington DC";
farms.StateName(dcRow) = "District of Columbia";
```

Join the tables, using the state name variables Name and StateName as the key variables. Display the first row of the joined table.

```
statesFarms = outerjoin(states, farms, "LeftKey", "Name", "RightKey", "StateName");
statesFarms(1,:)
ans=1×9 table
                                   LabelLat
                                                            PopDens2000
                                                                                          NumberOfFari
       Shape
                       Name
                                               LabelLon
                                                                            StateName
                     "Alabama"
                                    32.283
                                                -86.921
                                                               87.6
                                                                            "Alabama"
                                                                                              38800
    geopolyshape
```

For more information about how to combine vector data using table joins, see "Combine Vector Data Using Table Joins" on page 2-23.

Discretize Data

Group the average farm size for each state into 4 bins of type categorical. View the unique bins.

```
n = 4;
[BinnedAverageFarmSize,E] = discretize(statesFarms.AverageFarmSize,n,"categorical");
bins = unique(BinnedAverageFarmSize)
bins = 4×1 categorical
    [0, 700)
    [700, 1400)
    [1400, 2100)
    [2100, 2800]
```

Add the binned data to the geospatial table.

```
statesFarms = addvars(statesFarms,BinnedAverageFarmSize);
```

Create Map

Display the binned average farm size for states in the conterminous US by creating a classification map with a legend.

Set up a topographic map.

```
figure
geobasemap topographic
hold on
```

To include each bin in the legend as a separate data series, you must separately plot the states within each bin. For each bin:

- Find the indices of the table rows that are associated with the bin.
- Extract the rows into a subtable.
- Plot the data within the subtable, using the bin as the display name.


```
for k = 1:n
    idx = statesFarms.BinnedAverageFarmSize == bins(k);
    subT = statesFarms(idx,:);
    geoplot(subT,DisplayName=string(bins(k)))
end
```

Update the geographic limits to include the region surrounding the conterminous US. Add a title and legend.

```
geolimits([27 52],[-130 -60])
title("Average Farm Size Per US State in 2019")
lgd = legend;
title(lgd, "Size in Acres")
```

Change the colormap and increase the opacity of the states.


```
gx = gca;
gx.ColorOrder = parula(n);
alpha(0.75)
```



Export Map

Export the map to a PNG file.

gx = gca; exportgraphics(gx,"AverageFarmSizeClassification.png")



References

[1] National Agricultural Statistics Service. "Number of Farms, Land in Farms, and Average Farm Size — States and United States: 2018–2019." *In Farms and Land in Farms 2019 Summary*, 6. USDA, February 2020. https://www.nass.usda.gov/Publications/Todays Reports/reports/fnlo0220.pdf.

See Also

Functions

readgeotable | geoplot | colormap

Properties

Point Properties | Line Properties | Polygon Properties

Related Examples

- "Create Geospatial Tables" on page 2-18
- "Create Choropleth Map from Table Data" on page 6-7


Create Choropleth Map of Population Density

This example shows how to create a choropleth map of population density for the six New England states in the year 2000.

Import low-resolution U.S. state boundary polygons, setting the map limits for the New England region.

Set up an axesm-based map with a projection suitable to display the New England states.

```
figure
axesm('MapProjection', 'eqaconic', 'MapParallels', [],...
   'MapLatLimit', MapLatLimit, 'MapLonLimit', MapLonLimit,...
   'GLineStyle', '-')
geoshow(NEstates, 'DisplayType', 'polygon', 'FaceColor','green')
```



Identify the maximum population density for New England states.

```
maxdensity = max([NEstates.PopDens2000])
maxdensity = 1.0032e+03
```

Create an autumn colormap for the six New England states, and then use the flipud command to invert the matrix.

```
fall = flipud(autumn(height(NEstates)));
```


Make a symbol specification structure, a symbol spec, that assigns an autumn color to each polygon according to the population density.

```
densityColors = makesymbolspec('Polygon', {'PopDens2000', ...
  [0 maxdensity], 'FaceColor', fall});

Display the map.


geoshow(NEstates, 'DisplayType', 'polygon', ...
  'SymbolSpec', densityColors)
title ({'Population Density in New England in 2000', ...
  'in Persons per Square Mile'})
```

Population Density in New England in 2000 in Persons per Square Mile



Add a colorbar. You can also experiment with other colormaps.

```
caxis([0 maxdensity])
colormap(fall)
colorbar
```



See Also

Functions

axesm | geoshow | colormap

Related Examples

- "Create Choropleth Map from Table Data" on page 6-7
- "Create Classification Map from Table Data" on page 6-11

Scale Maps for Printing

Maps are often printed at a size that makes objects on paper a particular fraction of their real size. The linear ratio of the mapped to real object sizes is called $map\ scale$, and it is usually notated with a colon as "1:1,000,000" or "1:24,000." Another way of specifying scale is to call out the printed and real lengths, for example "1 inch = 1 mile."

You can specify the printed scale using the paperscale function. It modifies the size of the printed area on the page to match the scale. If the resulting dimensions are larger than your paper, you can reduce the amount of empty space around the map using tightmap or zoom, and by changing the axes position to fill the figure. This also reduces the amount of memory needed to print with the zbuffer (raster image) renderer. Be sure to set the paper scale last. For example,

```
set(gca, 'Units', 'Normalized', 'Position',[0 0 1 1])
tightmap
paperscale(1, 'in', 5, 'miles')
```

The paperscale function also can take a scale denominator as its first and only argument. If you want the map to be printed at 1:20,000,000, type

```
paperscale(2e7)
```

To check the size and extent of text and the relative position of axes, use previewmap, which resizes the figure to the printed size.

```
previewmap
```

For more information on printing, see "Printing and Saving".

Create Common Plots over Basemap Images

When you create maps using geographic axes, you can provide context for your data by specifying a basemap. Geographic axes support several types of plots, including point, line, and polygon plots (geoplot), scatter plots (geoscatter), density plots (geodensityplot), and bubble plots (geobubble or bubblechart).

When geographic axes do not support a type of plot, you can read an image from a basemap by using the readBasemapImage function and then display both the image and the plot over an axes. This topic includes examples for displaying these types of plots over basemap images:

- Digraphs on page 6-19
- Contours on page 6-21
- Images on page 6-23
- 3-D surfaces on page 6-24

Digraphs

This example shows how to display a digraph of airport traffic over a basemap image.

Load Data

Specify the codes and geographic coordinates of five US airports.

```
code = ["DEN" "LAS" "LAX" "SEA" "SFO"];
lat = [39.8561 36.1699 33.9416 47.4502 37.6213];
lon = [-104.6737 -115.1398 -118.4085 -122.3088 -122.379];
```

Create a digraph from a table containing airport traffic data. Reorder the digraph nodes to match the order in code.

- The Origin and Dest table variables contain codes for the origin airports and destination airports.
- The NumFlights variable table contains the number of flights between the origin and destination airport.

```
T = readtable("airport_traffic.xlsx");
G = digraph(T.Origin,T.Dest,T.NumFlights);
G = reordernodes(G,code);
```

Read Basemap Image

Specify latitude and longitude limits for the basemap image. Find the limits for the region containing the airports by using the geoquadline function. Expand the limits by 2 degrees in latitude and 3 degrees in longitude by using the bufgeoquad function.

```
[latlim,lonlim] = geoquadline(lat,lon);
[latlim,lonlim] = bufgeoquad(latlim,lonlim,2,3);
```

Read an image for the region from the "landcover" basemap, using a zoom level of 5, as an array and a map cells reference object.

```
[A,RA] = readBasemapImage("landcover", latlim, lonlim, 5);
```

Project Data to Web Mercator Coordinates

The readBasemapImage function spatially references basemap images by using a Web Mercator (WGS 84 / Pseudo-Mercator) projected coordinate reference system (CRS). Project the airport locations from geographic coordinates to Web Mercator coordinates.

```
[x,y] = projfwd(RA.ProjectedCRS,lat,lon);
```

Display Data over Basemap Image

Display the basemap image on a map with no axis labels.

```
figure
mapshow(A,RA)
hold on
axis off
```

Display the digraph on the same map. Customize the digraph plot using these options:

- Position the nodes by setting the *x*-data and *y*-data properties to the projected airport coordinates.
- Use thicker edges for more heavily trafficked routes by setting the line width property.
- Improve the visibility of the plot by setting the node font size, edge transparency, arrow size, edge color, and node color properties.

```
lineWidth = G.Edges.Weight/min(G.Edges.Weight);
plot(G,XData=x,YData=y,LineWidth=lineWidth, ...
    NodeFontSize=11,EdgeAlpha=0.6,ArrowSize=12, ...
    EdgeColor="#A2142F",NodeColor="#A2142F")

Add a title and subtitle.

title("Airport Traffic for Five US Airports")
subtitle("Basemap Attribution: Natural Earth")
```

SEA DEN

Airport Traffic for Five US Airports

Basemap Attribution: Natural Earth

Contours

This example shows how to display contours of the Earth Gravitational Model of 1996 (EGM96) over a basemap image.

Load Data

Load geoid heights from EGM96 for a region containing the conterminous United States. The egm96geoid function returns geoid heights as an array and a geographic cells reference object in WGS 84 coordinates.

```
latlim = [17 56];
lonlim = [-128 -64];
[N,RN] = egm96geoid;
[N,RN] = geocrop(N,RN,latlim,lonlim);
```

To read spatially referenced raster data from a file, use the readgeoraster function.

Read Basemap Image

Read an image for the region from the "satellite" basemap as an array, a map cells reference object, and an attribution string.

```
[A,RA,attrib] = readBasemapImage("satellite",latlim,lonlim);
```

Project Data to Web Mercator Coordinates

The readBasemapImage function spatially references basemap images by using a Web Mercator (WGS 84 / Pseudo-Mercator) projected CRS. To display the geoid heights over the basemap image, you must project the geographic coordinates to the projected CRS.

Extract the geographic coordinates of the geoid heights from the reference object. Then, project the geographic coordinates to Web Mercator coordinates.

```
[lat,lon] = geographicGrid(RN);
[x,y] = projfwd(RA.ProjectedCRS,lat,lon);
```

Display Data over Basemap Image

Display the basemap image on a map with no axis labels.

```
figure
mapshow(A,RA)
hold on
axis off
```

Display 10 contours of the geoid heights on the same map.


```
contour(x,y,N,10,LineWidth=1.5)
```

Add a title and subtitle.

```
title("Contours of EGM96")
subtitle("Basemap Attribution: " + attrib)
```

Contours of EGM96

Basemap Attribution: Earthstar Geographics



Images

This example shows how to display an icon of the L-shaped membrane over a basemap image containing the MathWorks® Lakeside Campus in Natick, MA.

Read Basemap Image

Read an image of size 800-by-1000 from the "streets-dark" basemap for a region centered on the Lakeside Campus. The readBasemapImage function returns the basemap image as an array, a map cells reference object, and an attribution string.

```
lat = 42.3010;
lon = -71.3751;
[A,RA,attrib] = readBasemapImage("streets-dark",[lat lon],16,[800 1000]);
```

Load Icon

Read the icon as an indexed image of size 16-by-16 and a colormap. To improve visibility on the map, increase the image size by a factor of 4.

```
[M,cmap] = imread(fullfile(matlabroot, "toolbox", "matlab", "icons", "matlabicon.gif"));
[M,cmap] = imresize(M,cmap,4);
```

Spatially Reference Icon

The readBasemapImage function spatially references basemap images by using a Web Mercator (WGS 84 / Pseudo-Mercator) projected CRS. Using the coordinates of the Lakeside Campus as the lower-left corner of the image, spatially reference the icon to Web Mercator coordinates.

Project the latitude and longitude coordinates of the Lakeside Campus to Web Mercator coordinates.

```
[x,v] = projfwd(RA.ProjectedCRS,lat,lon);
```

Specify the *xy*-limits of the icon using the projected coordinates, the size of the icon, and the sizes of individual cells in the basemap image.

```
sz = size(M);
xlimits = [x (x + sz(2)*RA.CellExtentInWorldX)];
ylimits = [y (y + sz(1)*RA.CellExtentInWorldY)];
```

Spatially reference the icon by creating a map cells reference object. Indicate that the first row of the image is the northmost row (as is common with images) by setting the ColumnsStartFrom property.

```
RM = maprefcells(xlimits,ylimits,sz,ColumnsStartFrom="north");
```

Display Data over Basemap Image

Display the basemap image on a map with no axis labels.

```
figure
mapshow(A,RA)
hold on
axis off
```

Display the icon on the same map.

```
mapshow(M,cmap,RM)
```

Add a title and subtitle. Wrap the basemap attribution text.

```
title("Location of Lakeside Campus")
t = "Basemap Attribution: " + attrib;
t = string(textwrap(t,55));
subtitle(t)
```

Location of Lakeside Campus

Basemap Attribution: MassGIS, Esri, HERE, Garmin, GeoTechnologies, Inc., Intermap, USGS, EPA



3-D Surfaces

This example shows how to display a sample 3-D surface over a basemap image.

Load Data

Create a sample 3-D surface referenced to geographic coordinates. Generate the z-coordinates by using the peaks function. Reference the z-coordinates to a region in latitude-longitude coordinates by using the georefcells function.

```
Z = 100*peaks;
RZ = georefcells([42.3342 42.3561],[-73.3191 -73.2847],size(Z));
```

To read spatially referenced raster data from a file, use the readgeoraster function.

Read Basemap Image

Specify latitude and longitude limits for the basemap image by expanding the 2-D limits of the surface. For this example, expand the limits by 0.01 degrees.

```
[latlim,lonlim] = bufgeoquad(RZ.LatitudeLimits,RZ.LongitudeLimits,0.01,0.01);
```

Read an image from the "streets" basemap as an array, a map cells reference object, and an attribution string.

```
[A,RA,attrib] = readBasemapImage("streets",latlim,lonlim);
```

Project Data to Web Mercator Coordinates

The readBasemapImage function spatially references basemap images by using a Web Mercator (WGS 84 / Pseudo-Mercator) projected CRS. To display the surface over the basemap image, you must project the geographic coordinates to the projected CRS.

Extract the geographic coordinates of the surface from the reference object. Then, project the geographic coordinates to Web Mercator coordinates.

```
[lat,lon] = geographicGrid(RZ);
[x,y] = projfwd(RA.ProjectedCRS,lat,lon);
```

Display Data over Basemap Image

Display the basemap image on a map with no axis labels.

```
figure
mapshow(A,RA)
hold on
axis off

Display the 3-D surface on the same map.

surf(x,y,Z)
view(3)


Add a title and subtitle. Wrap the basemap attribution text.

title("3-D Surface Over Basemap")

t = "Basemap Attribution: " + attrib;
t = string(textwrap(t,55));
subtitle(t)
```

3-D Surface Over Basemap

Basemap Attribution: Esri, HERE, Garmin, GeoTechnologies, Inc., NGA, USGS



See Also

Functions

readBasemapImage | readgeoraster | projfwd

Objects

MapCellsReference | GeographicAxes Properties

Related Examples

- "Types of MATLAB Plots"
- "Change Projection of Basemap Image" on page 6-27

Change Projection of Basemap Image

Geographic axes display data over basemaps using a Web Mercator projected coordinate reference system (CRS). While the Mercator projection preserves angles and is suitable for small regions, it distorts areas and is not appropriate for large or polar regions.

To display data over a basemap using a different projection method, you can read an image from a basemap by using the readBasemapImage function and then change the projection using one of these options:

- Change Projection Using Projection Stored in axesm-Based Map on page 6-27 This option is convenient for projection methods supported by axesm-based maps.
- Change Projection Using Projected CRS Object on page 6-29 This option is useful for projection methods not supported by axesm-based maps.

Change Projection Using Projection Stored in axesm-Based Map

This example shows how to project a basemap image by using the projection method stored in an axesm-based map. For more information about projections supported by axesm-based maps, see "Summary and Guide to Projections" on page 8-45.

Load Data

Read the latitude and longitude coordinates of European capitals from a text file.

```
[lat,lon] = readvars("european capitals.txt");
```

Read Basemap Image

Specify latitude and longitude limits for the basemap image. Find the limits for the region containing the capitals by using the geoquadline function. Expand the limits by 10 degrees in latitude and longitude by using the bufgeoquad function.

```
[latlim,lonlim] = geoquadline(lat,lon);
[latlim,lonlim] = bufgeoquad(latlim,lonlim,10,10);
```

Read an image for the region from the "bluegreen" basemap, using a zoom level of 3, as an array and a map cells reference object in Web Mercator coordinates.

```
[A,RA] = readBasemapImage("bluegreen", latlim, lonlim, 3);
```

Unproject Basemap Image

Extract the Web Mercator coordinates of the basemap image from the reference object. Then, unproject the coordinates to geographic coordinates.

```
[xGrid,yGrid] = worldGrid(RA);
[latGrid,lonGrid] = projinv(RA.ProjectedCRS,xGrid,yGrid);
```

The coordinates of the European capitals are already in geographic coordinates. If you are adapting this example to your own code and your data is in projected coordinates, you must unproject your data to geographic coordinates.

Create Map

Create an axesm-based map with a projection that is suitable for the region by using the worldmap function. Alternatively, you can create an axesm-based map with a specified projection ID by using the axesm function.

```
figure
h = worldmap(latlim,lonlim);
View the projection method stored in the map.
getm(h, "mapprojection")
ans =
'egdconic'
```

The result 'eqdconic' means that the map uses an Equidistant Conic projection.

Display the basemap and the European capitals on the map. The geoshow function projects and displays the latitude-longitude coordinates of the basemap image and capitals using the projection method stored in the map.

European Capitals

```
geoshow(latGrid,lonGrid,A)
geoshow(lat,lon,DisplayType="point",Marker="pentagram")
title("European Capitals")
subtitle("Basemap Attribution: Natural Earth")
```

Basemap Attribution: Natural Earth 60° 50° 40° 10° W 30° E o° 20° E

10° E

Text in the projected basemap image can appear distorted.

Change Projection Using Projected CRS Object

This example shows how to read a basemap image using a projected CRS object and then display the projected image on an axes.

Load Data

Read a shapefile containing the coordinates of world cities into the workspace as a geospatial table. Extract the latitude and longitude coordinates.

```
GT = readgeotable("worldcities.shp");
lat = GT.Shape.Latitude;
lon = GT.Shape.Longitude;
```

Specify Projected CRS and Find Area of Use

Specify the projected CRS you want to use. For this example, create a projers object for WGS 84 / Equal Earth Asia-Pacific, which has the EPSG code 8859.

```
equalEarth = projcrs(8859);
```

Different projected CRSs are valid for different areas of use. For many projected CRSs, you can find the area of use by displaying the well-known text (WKT) string of the CRS and finding the BBOX attribute. This WKT specifies BBOX in the second-to-last line.

```
wktstring(equalEarth,Format="formatted")
```

```
ans =
    "PROJCRS["WGS 84 / Equal Earth Asia-Pacific",
         BASEGEOGCRS["WGS 84",
             DATUM["World Geodetic System 1984",
                 ELLIPSOID["WGS 84",6378137,298.257223563,
                     LENGTHUNIT["metre",1]]],
             PRIMEM["Greenwich",0,
                 ANGLEUNIT["degree", 0.0174532925199433]],
             ID["EPSG",4326]],
         CONVERSION["Equal Earth Asia-Pacific",
             METHOD["Equal Earth",
                 ID["EPSG", 1078]],
             PARAMETER["Longitude of natural origin", 150,
                 ANGLEUNIT["degree", 0.0174532925199433],
                 ID["EPSG",8802]],
             PARAMETER["False easting",0,
                 LENGTHUNIT["metre",1],
                 ID["EPSG",8806]],
             PARAMETER["False northing",0,
                 LENGTHUNIT["metre",1],
                 ID["EPSG",8807]]],
         CS[Cartesian,2],
             AXIS["(E)",east,
                 ORDER[1],
                 LENGTHUNIT["metre",1]],
             AXIS["(N)", north,
                 ORDER[2],
                 LENGTHUNIT["metre",1]],
             SCOPE["Very small scale equal-area mapping - Asia-Pacific-centred."],
             AREA["World centred on Asia-Pacific."],
```

```
BBOX[-90,-29.99,90,-30.01]],
ID["EPSG",8859]]"
```

Specify the latitude and longitude limits for the basemap image by using the information in BBOX. For this projected CRS, unwrap the maximum longitude by adding 360 degrees to the minimum longitude.

```
latlim = [-90 90];
lonmin = -29.99;
lonlim = [lonmin lonmin+360];
```

Read Basemap Image

Read an image from the "satellite" basemap as an array, a map cells reference object in Web Mercator coordinates, and an attribution string.

```
[A,RA,attrib] = readBasemapImage("satellite",latlim,lonlim);
```

Reproject Data and Basemap Image

Reproject the coordinates of the basemap image to Equal Earth coordinates.

- Extract the Web Mercator coordinates of the basemap image from the reference object.
- Unproject the Web Mercator coordinates to geographic coordinates.
- Project the geographic coordinates to Equal Earth coordinates.

```
[xGrid,yGrid] = worldGrid(RA);
[latGrid,lonGrid] = projinv(RA.ProjectedCRS,xGrid,yGrid);
[xEqualEarth,yEqualEarth] = projfwd(equalEarth,latGrid,lonGrid);
```

Project the geographic coordinates of the world cities to Equal Earth coordinates. If you are adapting this example to your own code and your data is in projected coordinates, you must first unproject your data to geographic coordinates.


```
[xData,yData] = projfwd(equalEarth,lat,lon);
```

Create Map

Display the projected basemap image and world cities on a map with no axis labels.

```
figure
mapshow(xEqualEarth,yEqualEarth,A)
hold on
mapshow(xData,yData,DisplayType="point",Marker=".")
title("World Cities")
subtitle("Basemap Attribution: " + attrib)
axis off
```

World Cities
Basemap Attribution: Earthstar Geographics



Text in the projected basemap image can appear distorted.

See Also

Functions

readBasemapImage | worldmap | geoshow | mapshow | projfwd | projinv

Objects

MapCellsReference | projcrs

Related Examples

• "Create Common Plots over Basemap Images" on page 6-19

Use Basemaps in Offline Environments

Provide geographic context for your maps by displaying data over a basemap, also called a base layer. MathWorks provides a variety of basemaps, including low-resolution two-tone options created using Natural Earth and high-zoom-level options hosted by Esri. For a list of basemap options, see the basemap argument of the geobasemap function.

Most of these basemaps require internet access, including the default basemap. If you do not have reliable access to the internet, you can use strategies such as downloading a selection of basemaps onto your local system or displaying data over the "darkwater" basemap. Some strategies require MATLAB to have temporary internet access and other strategies do not require MATLAB to have internet access. Different strategies support different types of map displays.

Internet Access Requirement for MATLAB	Strategy	Supported Map Displays
"Temporary Internet Access" on page 6-32	Download basemaps onto your local system on page 6-0	Objects with a Basemap property, for example:
		 Geographic axes Geographic globes Site Viewer (Communications Toolbox™, Antenna Toolbox™) Satellite Scenario Viewer (Satellite
	Use cached basemap tiles on page 6-0	Communications Toolbox)Geographic axesGeographic bubble charts
	Use a spatially referenced image from a web source on page 6-0	Axes (mapshow) axesm-based maps (geoshow)
"No Internet Access" on page 6-36	Create a basemap from an MBTiles file on page 6-0	Objects with a Basemap property
	Use a basemap installed with MATLAB® on page 6-0	Objects with a Basemap property
	Use a spatially referenced image from a file on page 6-0	Axes (mapshow) axesm-based maps (geoshow)
	Use spatially referenced vector data from a file on page 6-0	Geographic axes (geoplot) Axes (mapshow) axesm-based maps (geoshow)

Temporary Internet Access

These strategies require MATLAB to temporarily access the internet. When MATLAB is in an online environment, you can save the basemap data to your local system. Then, when MATLAB is in an offline environment, you can load the saved basemap data.

- Download basemaps onto your local system on page 6-33
- Use cached basemap tiles on page 6-33
- Use a spatially referenced image from a web source on page 6-33

Download basemaps onto your local system

When you have internet access, you can download the basemaps created using Natural Earth onto your local system. The basemaps hosted by Esri are not available for download. Then, when you are in an offline environment, you can use the downloaded basemaps.

Download basemaps using the Add-On Explorer.

- 1 On the MATLAB **Home** tab, in the **Environment** section, click **Add-Ons** and then **Get Add-Ons**.
- In the Add-On Explorer, scroll to the MathWorks Optional Features section, and click Show All to find the basemap add-ons. You can also search for the basemap add-ons by name, or click Optional Features in Filter by Type.
- **3** Select the basemap add-ons that you want to download.

These are the names of the basemap add-ons and their associated basemap argument names.

- MATLAB Basemap Data bluegreen ("bluegreen")
- MATLAB Basemap Data grayland ("grayland")
- MATLAB Basemap Data colorterrain ("colorterrain")
- MATLAB Basemap Data grayterrain ("grayterrain")
- MATLAB Basemap Data landcover ("landcover")

Use cached basemap tiles

When you view a basemap over the internet, MATLAB temporarily caches the basemap tiles. If you lose your internet connection, you can still view the cached basemap tiles.

When you are in an offline environment and attempt to view basemap tiles that you have not previously viewed, MATLAB issues a warning and displays different tiles depending on the type of basemap. When you attempt to view tiles created using Natural Earth, MATLAB displays "darkwater" tiles. When you attempt to view tiles from a custom basemap or tiles hosted by Esri, you see missing map tiles.

Cached basemap tiles have these limitations:

- MATLAB stores the cached tiles in a temporary folder. Your operating system can delete the temporary folder.
- The cached tiles can expire.
- MATLAB caches custom basemap tiles for only the current MATLAB session.

Use a spatially referenced image from a web source

When you have internet access, you can read an image from a basemap or a Web Map Service (WMS) server as a spatially referenced image and save the image as a MAT or GeoTIFF file. Then, when you

are in an offline environment, you can load the image from the file and use it as a base layer for your data.

Read and save an image from a basemap

Read satellite imagery for Boston into the workspace as an array, a map cells reference object, and an attribution by using the readBasemapImage function.

```
[A1,R1,attrib1] = readBasemapImage("satellite",[42.3453 42.3711],[-71.099 -71.0454]);
```

Save the imagery as a GeoTIFF file by using the geotiffwrite function.

- The readBasemapImage function spatially references the image using the Web Mercator projected coordinate reference system (CRS) with EPSG code 3857. Specify the CRS code by using the CoordRefSysCode name-value argument.
- Include the attribution by specifying the ImageDescription TIFF tag.

```
tag = struct("ImageDescription",attrib1);
geotiffwrite("satelliteBoston.tif",A1,R1,CoordRefSysCode=3857,TiffTags=tag)
```


To use the basemap data, load the GeoTIFF file and attribution.

```
[A2,R2] = readgeoraster("satelliteBoston.tif");
info = imfinfo("satelliteBoston.tif");
attrib2 = info.ImageDescription;
```

Display the data on a map. Use the mapshow function when the reference object is a map reference object and use the geoshow function when the reference object is a geographic reference object.

```
figure
mapshow(A2,R2)
title("Boston Imagery from Basemap")
subtitle("Attribution: " + attrib2)
axis off
```

Boston Imagery from Basemap





For more information about displaying data over basemaps images in offline environments, see "Display Data over Basemaps When Internet Access Is Intermittent" on page 6-42.

Read and save an image from a WMS server

WMS servers provide publicly accessible geospatial data from web-based sources. Search the WMS Database for orthoimagery from the USGS National Map.

```
usgs = wmsfind("basemap.nationalmap", SearchFields="ServerURL");
imagery = refine(usgs, "USGSImageryOnly", SearchFields="ServerURL");
imagery = wmsupdate(imagery);
```

Read orthoimagery for an area in Boston and save it as a GeoTIFF file.

```
 [A3,R3] = wmsread(imagery,Latlim=[42.3453\ 42.3711],Lonlim=[-71.099\ -71.0454]); \\ geotiffwrite("usgsImageryLayer.tif",A3,R3)
```

To use the WMS orthoimagery, load the GeoTIFF file and display it on a map.

```
[A4,R4] = readgeoraster("usgsImageryLayer.tif");
figure
usamap(A4,R4)
geoshow(A4,R4)
title("Boston Imagery from WMS Server")
subtitle("Attribution: USGS National Map")
```

Boston Imagery from WMS Server

Attribution: USGS National Map



For more information about creating WMS maps in offline environments, see "Create WMS Maps When Internet Access Is Intermittent" on page 9-51.

No Internet Access

These strategies do not require MATLAB to access the internet.

- Create a basemap from an MBTiles file on page 6-36
- Use "darkwater" basemap installed with MATLAB on page 6-37
- Use a spatially referenced image from a file on page 6-38
- Use spatially referenced vector data from a file on page 6-39

Create a basemap from an MBTiles file

When you are in an offline environment, you can create custom basemaps from MBTiles files that contain tile sets of raster data. Create custom basemaps from MBTiles files by using the addCustomBasemap function.

Mapping Toolbox™ includes an MBTiles file with low-resolution USGS imagery called usgsimagery.mbtiles. Create a custom basemap from the file and display it over a geographic globe. Position the camera 3200 kilometers above Boston.

addCustomBasemap("usgsimagery", "usgsimagery.mbtiles")

```
uif = uifigure;
g = geoglobe(uif);
geobasemap(g,"usgsimagery")
campos(g,42.3582,-71.0722,3200000)
```




Use "darkwater" basemap installed with MATLAB

MATLAB includes the "darkwater" basemap, a two-tone land-ocean map with light gray land areas and dark grey water areas. Using the "darkwater" basemap does not require internet access.

Display the "darkwater" basemap over a geographic axes. Center the map over the northeast United States.

```
figure
geobasemap darkwater
geolimits([40.1951 47.8433],[-77.5238 -64.0377])
title("Northeast United States with Darkwater Basemap")
subtitle("Attribution: Natural Earth")
```

Northeast United States with Darkwater Basemap




Use a spatially referenced image from a file

When you are in an offline environment, you can read a spatially referenced raster image from a file and then use it as a base layer for your data. The function you use to read the data depends on the file format.

- Read images in formats such as GeoTIFF by using the readgeoraster function.
- Read images in formats such as TIFF, JPEG, or PNG that are associated with a world file by using the imread and worldfileread functions.

Read a GeoTIFF image of Boston into the workspace as an array and a map cells reference object. Then, display the image on a map. Use the mapshow function when the reference object is a map reference object and use the geoshow function when the reference object is a geographic reference object.

```
[A5,R5] = readgeoraster("boston.tif");
figure
mapshow(A5,R5)
title("Boston Imagery from GeoTIFF File")
subtitle("Attribution: GeoEye")
```




Use spatially referenced vector data from a file

When you are in an offline environment, you can read spatially referenced vector data from a file and then use it as a base layer for your data. Read vector data in formats such as shapefile by using the readgeotable function.

Mapping Toolbox $^{\text{m}}$ includes a shapefile with world land areas called landareas.shp. Read the land areas into the workspace as a geospatial table. Then, display the land areas on a world map.

```
GT = readgeotable("landareas.shp");
figure
worldmap world
geoshow(GT)
title("World Land Areas from Shapefile")
```




Mapping Toolbox™ includes shapefiles with high- and low-resolution US state boundaries called usastatehi.shp and usastatelo.shp, respectively. Read the high-resolution state boundaries into the workspace as a geospatial table. Clip the boundaries to include only the northeast states.

```
GT = readgeotable("usastatehi.shp");
ne = geoclip(GT.Shape,[40.1951 47.8433],[-77.5238 -64.0377]);
```

Display the boundaries on a geographic axes. To prevent MATLAB from using the basemaps provided by MathWorks, set the basemap to "none".

```
figure
geobasemap none
hold on
geoplot(ne)
title("Northeast United States from Shapefile")
```



See Also

Functions

geobasemap|geotiffwrite|wmsread

Related Examples

- "Access Basemaps for Geographic Axes and Charts"
- "Access Basemaps and Terrain for Geographic Globe" on page 5-68

Display Data over Basemaps When Internet Access Is Intermittent

In most cases, displaying data over basemaps requires internet access. When you have intermittent internet access, you can prepare for an offline workflow by reading an image from a basemap and saving the image as a MAT or GeoTIFF file. Then, when you are in an offline environment, you can load the image from the file and use it as a base layer for your data.

This example shows how plot point data over a basemap image. The behavior of the example depends on whether you have internet access, but the resulting map is the same.

Specify whether you have internet access by using the logical scalar useInternet.

- If useInternet is true, read an image from the basemap and save it to a GeoTIFF file.
- If useInternet is false, read an image from a GeoTIFF file.

```
useInternet = true;
```

If you use this example as a model to create your own maps, you must create the saved files the first time you run the example by setting useInternet to true.

Load Data

Import a shapefile containing the coordinates of locations in Boston as a geospatial table. The shapefile represents the locations using points in a projected coordinate reference system (CRS). Extract the *xy*-coordinates.

Read Basemap

When you read an image from a basemap using the readBasemapImage function, you must specify the region to read using geographic coordinates. For this example, however, the locations are in projected coordinates. Unproject the *xy*-coordinates to latitude-longitude coordinates.

```
[pointslat,pointslon] = projinv(pointsCRS,pointsX,pointsY);
```

Find the latitude-longitude limits for a region surrounding the coordinates by using the geoquadline and bufgeoquad functions.

```
[latlim,lonlim] = geoquadline(pointslat,pointslon);
[latlim,lonlim] = bufgeoquad(latlim,lonlim,0.005,0.005);
```

Read a basemap image for the region from the "satellite" basemap.

- If useInternet is true, read the basemap image as an array, a map cells reference object in Web Mercator coordinates (EPSG code 3857), and an attribution string. Save the array and reference object to a GeoTIFF file. Include the attribution by specifying the ImageDescription TIFF tag.
- If useInternet is false, load the basemap image and attribution.

```
if useInternet
    [A,R,attrib] = readBasemapImage("satellite",latlim,lonlim);
    tag = struct("ImageDescription",attrib);
    geotiffwrite("satelliteBoston.tif",A,R,CoordRefSysCode=3857,TiffTags=tag)
else
    [A,R] = readgeoraster("satelliteBoston.tif");
    info = imfinfo("satelliteBoston.tif");
    attrib = info.ImageDescription;
end
```

Project Data to Web Mercator Coordinates

Project the geographic coordinates to the same CRS as the basemap image.

```
[wmX,wmY] = projfwd(R.ProjectedCRS,pointslat,pointslon);
```

Display Data over Basemap Image

Display the basemap image on a map with no axis labels.

```
figure
mapshow(A,R)
hold on
axis off
```

Display the locations on the same map.

```
mapshow(wmX,wmY,DisplayType="point",Marker="o",MarkerFaceColor="r")
title("Locations in Boston Over Satellite Imagery")
subtitle("Basemap Attribution: " + attrib)
```

Locations in Boston Over Satellite Imagery

Basemap Attribution: Maxar



The geographic CRS underlying the geographic coordinates is NAD83, while the geographic CRS underlying the basemap image is WGS84. NAD83 and WGS84 are similar, but not identical. As a result, the coordinates and basemap can appear misaligned.

See Also

Functions

readBasemapImage | geotiffwrite | readgeoraster

Objects

MapCellsReference | projcrs

Related Examples

- "Use Basemaps in Offline Environments" on page 6-32
- "Create WMS Maps When Internet Access Is Intermittent" on page 9-51


Manipulating Geospatial Data

For some purposes, geospatial data is fine to use as is. Sooner or later, though, you need to extract, combine, massage, and transform geodata. This chapter discusses some Mapping Toolbox tools and techniques provided for such purposes.

- "Geographic Interpolation of Vectors" on page 7-2
- "Vector Intersections" on page 7-4
- "Polygon Set Logic" on page 7-6
- "Polygon Buffer Zones" on page 7-7
- "Simplify Vector Coordinate Data" on page 7-10
- "Convert Vector Data to Raster Format" on page 7-11
- "Data Grids as Logical Variables" on page 7-16

Geographic Interpolation of Vectors


When using vector data, remember that, like raster data, coordinates are sampled measurements. This involves unavoidable assumptions concerning what the geographic reality is between specified data points. The normal assumption when plotting vector data requires that points be connected with straight line segments, which essentially indicates a lack of knowledge about conditions between the measured points. For lines that are by nature continuous, such as most rivers and coastlines, such piecewise linear interpolation can be false and misleading, as the following figure depicts.



Interpolating Sparse Vector Data

Despite the possibility of misinterpretation, circumstances do exist in which geographic data interpolation is useful or even necessary. To do this, use the interpm function to interpolate between known data points. One value of linearly interpolating points is to fill in lines of constant latitude or longitude (e.g., administrative boundaries) that can curve when projected.

interpm returns both the original data and new linearly interpolated points. Sometimes, however,
you might want only the interpolated values. The functions intrplat and intrplon work similarly
to the MATLAB interp1 function, and give you control over the method used for interpolation. Note
that they only interpolate and return one value at a time. Use intrplat to interpolate a latitude for a
given longitude. Given a monotonic set of longitudes and their matching latitude points, you can
interpolate a new latitude for a longitude you specify, interpolating along linear, spline, cubic, rhumb
line, or great circle paths. The longitudes must increase or decrease monotonically. If this is not the
case, you might be able to use the intrplon companion function if the latitude values are
monotonic. The following diagram illustrates these three types of interpolation. The intrplat
function also can perform spline and cubic spline interpolations.




Three Types of Interpolation

Vector Intersections


Mapping Toolbox includes a set of functions that calculate the intersections of vector data, such as great circles, small circles, and rhumb line tracks. The functions also determine intersections of arbitrary vector data.

Function	Description	
gcxgc	Find intersection points for pairs of great circles on the sphere	
scxsc	Find intersection points for pairs of small circles on the sphere	
rhxrh	Find intersection points, if any, for pairs of rhumb lines	
gcxsc	Find intersection points, if any, between a great circle and a small circle on the sphere	
polyxpoly	Find intersection points for lines or polygon edges in the plane	

In general, small circles intersect twice or never, as shown in the following figure. For the case of exact tangency, scxsc returns two identical intersection points.




To illustrate finding the intersection of rhumb lines, imagine a ship setting sail from Norfolk, Virginia (37°N,76°W), maintaining a steady due-east course (90°), and another ship setting sail from Dakar, Senegal (15°N,17°W), with a steady northwest course (315°). Where would the tracks of the two vessels cross? The intersection of the tracks is at (37°N,41.7°W), which is roughly 600 nautical miles west of the Azores in the Atlantic Ocean.



See Also

Polygon Set Logic

Polygon set operations are used to answer a variety of questions about logical relationships of vector data polygon objects. Standard set operations include intersection, union, subtraction, and an exclusive OR operation. The polybool function performs these operations on two sets of vectors, which can represent x-y or latitude-longitude coordinate pairs. In computing points where boundaries intersect, interpolations are carried out on the coordinates as if they were planar. Here is an example that shows all the available operations.



The result is returned as NaN-clipped vectors by default. In cases where it is important to distinguish outer contours of polygons from interior holes, polybool can also accept inputs and return outputs as cell arrays. In the cell array format, a cell array entry starts with the list of points making up the outer contour. Subsequent NaN-clipped faces within the cell entry are interpreted as interior holes.

Polygon Buffer Zones

A *buffer zone* is the area within a specified distance of a map feature. For vector geodata, buffer zones are constructed as polygons. A buffer zone can be defined as the locus of points within a certain distance of the boundary of the feature polygon, either inside or outside the polygon. Buffer zones form equidistant contour lines around objects.

The bufferm function computes and returns vectors that represent a set of points that define a buffer zone. It forms the buffer by placing small circles at the vertices of the polygon and rectangles along each of its line segments, and applying a polygon union set operation to these objects.

Generate Buffer Internal to Polygon


This example shows how to use the bufferm function to generate a buffer zone internal to a land area polygon.

Import Madagascar polygon shape.

```
madagascar = shaperead('landareas.shp','UseGeoCoords',true, ...
    'Selector', {@(name)strcmpi(name,'Madagascar'),'Name'});


Create a map showing Madagascar.

figure
worldmap('madagascar')
geoshow(madagascar)
```



Use bufferm to create a buffer zone that extends 0.75 degrees inland from the coast of Madagascar.

```
madlat = madagascar.Lat;
madlon = madagascar.Lon;
bufwidth = 0.75;
direction = 'in';
[latbuf,lonbuf] = bufferm(madlat,madlon,bufwidth,direction);
Show the buffer zone in green.
geoshow(latbuf,lonbuf,'DisplayType','polygon','FaceColor','green')
```



Simplify Vector Coordinate Data

Avoiding visual clutter in composing maps is an essential part of cartographic presentation. In cartography, this is described as map generalization, which involves coordinating many techniques, both manual and automated. Limiting the number of points in vector geodata is an important part of generalizing maps, and is especially useful for conditioning cartographic data, plotting maps at small scales, and creating versions of geodata for use at small scales.

An easy, but naive, approach to point reduction is to discard every *n*th element in each coordinate vector (simple decimation). However, this can result in poor representations of the original shapes. The toolbox provides a function to eliminate insignificant geometric detail in linear and polygonal objects, while still maintaining accurate representations of their shapes. The reducem function implements a powerful line simplification algorithm (known as Douglas-Peucker) that intelligently selects and deletes visually redundant points.

The reducem function takes latitude and longitude vectors, plus an optional linear tolerance parameter as arguments, and outputs reduced (simplified) versions of the vectors, in which deviations perpendicular to local "trend lines" in the vectors are all greater than the tolerance criterion. Endpoints of vectors are preserved. Optional outputs are an error measure and the tolerance value used (it is computed when you do not supply a value).

Note Simplified line data might not always be appropriate for display. If all or most intermediate points in a feature are deleted, then lines that appear straight in one projection can be incorrectly displayed as straight lines in others, and separate lines can be caused to intersect. In addition, when you are reducing data over large world regions, the effective degree of reduction near the poles are less than that achieved near the equator, due to the fact that the algorithm treats geographic coordinates as if they were planar.

Convert Vector Data to Raster Format

You can convert latitude-longitude vector data to a grid at any resolution you choose to make a raster base map or grid layer. Certain Mapping Toolbox GUI tools help you do some of this, but you can also perform vector-to-raster conversions from the command line. The principal function for gridding vector data is vec2mtx, which allocates lines to a grid of any size you indicate, marking the lines with 1s and the unoccupied grid cells with 0s. The grid contains doubles, but if you want a logical grid (see "Data Grids as Logical Variables" on page 7-16) cast the result to be a logical array. To see an example, view "Creating Data Grids from Vector Data" on page 7-11.

If the vector data consists of polygons (patches), the gridded outlines are all hollow. You can differentiate them using the encodem function, calling it with an array of rows, columns, and seed values to produce a new grid containing polygonal areas filled with the seed values to replace the binary values generated by vec2mtx.

Creating Data Grids from Vector Data

This example shows how to convert vector data to raster data using the vec2mtx function. The example uses patch data for Indiana from the usastatehi shapefile. For more information, see "Convert Vector Data to Raster Format" on page 7-11.

Use shaperead to get the patch data for the boundary.


```
indiana = shaperead('usastatehi.shp',...
    'UseGeoCoords', true,...
    'Selector', {@(name)strcmpi('Indiana',name),'Name'});
inLat = indiana.Lat;
inLon = indiana.Lon;
```

Convert the vectors to a regular data grid using vec2mtx. Set the grid density to be 40 cells per degree. Rasterize the boundary and generate a geographic raster reference object for it.

```
gridDensity = 40;
[inGrid,R] = vec2mtx(inLat,inLon,gridDensity);
```


Make a map of the data grid in contrasting colors.

```
figure
axesm eqdcyl
meshm(inGrid,R)
colormap jet(4)
```



Set up the map limits.

setm(gca,'Flatlimit',R.LatitudeLimits,'FlonLimit',R.LongitudeLimits)
tightmap




Specify the seed point and seed value. To fill (recode) the interior of Indiana, you need a seed point (which must be identified by row and column) and a seed value (to be allocated to all cells within the polygon). Select the middle row and column of the grid and choose an index value of 3 to identify the territory when calling encodem to generate a new grid. The last argument (1) identifies the code for boundary cells, where filling should halt.

```
inPt = round([size(inGrid)/2,3]);
inGrid3 = encodem(inGrid,inPt,1);
```


Clear and redraw the map using the filled grid.

meshm(inGrid3,R)



Plot the original vectors on the grid to see how well data was rasterized. You can use the Zoom tool on the figure window to examine the gridding results more closely.

```
plotm(inLat,inLon,'k')
```



Data Grids as Logical Variables

You can apply logical criteria to numeric data grids to create *logical grids*. Logical grids are data grids consisting entirely of 1s and 0s. You can create them by performing logical tests on data grid variables. The resulting binary grid is the same size as the original grid(s) and can use the same referencing vector, as the following hypothetical data operation illustrates:

```
logicalgrid = (realgrid > 0);
```

This transforms all values greater than 0 into 1s and all other values to 0s. You can apply multiple conditions to a grid in one operation:

```
logicalgrid = (realgrid >- 100)&(realgrid < 100);</pre>
```

If several grids are the same size and share the same referencing vector (i.e., the grids are coregistered), you can create a logical grid by testing joint conditions, treating the individual data grids as map layers:

Several Mapping Toolbox functions enable the creation of logical grids using logical and relational operators. Grids resulting from such operations contain logical rather than numeric values (which reduce storage by a factor of 8), but might need to be cast to double in order to be used in certain functions. Use the ones and zeros functions to create grids of all 1s and all 0s.

Using Map Projections and Coordinate Systems

All geospatial data must be flattened onto a display surface in order to visually portray what exists where. The mathematics and craft of map projection are central to this process. Although there is no limit to the ways geodata can be projected, conventions, constraints, standards, and applications generally prescribe its usage. This chapter describes what map projections are, how they are constructed and controlled, their essential properties, and some possibilities and limitations.

- "Map Projections and Distortions" on page 8-2
- "Quantitative Properties of Map Projections" on page 8-4
- "The Three Main Families of Map Projections" on page 8-5
- "Projection Aspect" on page 8-9
- "Projection Parameters" on page 8-16
- "Visualize Spatial Error Using Tissot Indicatrices" on page 8-22
- "Quantify Map Distortions at Point Locations" on page 8-26
- "Rotational Transformations on the Globe" on page 8-30
- "Create a UTM Map" on page 8-34
- "Set UTM Parameters Interactively" on page 8-38
- "Work in UTM Without a Displayed Map" on page 8-41
- "Use the Transverse Aspect to Map Across UTM Zones" on page 8-43
- "Summary and Guide to Projections" on page 8-45
- "Transform Coordinates to a Different Projected CRS" on page 8-58
- "Project and Display Raster Data" on page 8-61

If you are not acquainted with the types, properties, and uses of map projections, read the first four sections. When constructing maps—especially in an environment in which a variety of projections are readily available—it is important to understand how to evaluate projections to select one appropriate to the contents and purpose of a given map.

Map Projections and Distortions

Humans have known that the shape of the Earth resembles a sphere and not a flat surface since classical times, and possibly much earlier than that. If the world were indeed flat, cartography would be much simpler because map projections would be unnecessary.

A map projection is a procedure that flattens a curved surface such as the Earth onto a plane. Usually this is done through an intermediate surface such as a cylinder or a cone, which is then unwrapped to lie flat. Consequently, map projections are classified as cylindrical, conical, and azimuthal (a direct transformation of the surface of part of a spheroid to a circle). See "The Three Main Families of Map Projections" on page 8-5 for discussions and illustrations of how these transformations work. The toolbox can project both vector data and raster data.

Get a map projection by using a projers object. For example, get information about a raster data file by creating a RasterInfo object. Then, find the projection method by querying the CoordinateReferenceSystem property of the object.

```
info = georasterinfo('boston.tif');
info.CoordinateReferenceSystem.ProjectionMethod
ans =
    "Lambert Conic Conformal (2SP)"
```

Alternatively, Mapping Toolbox includes a library of map projections that you can control with axesm and defaultm. Some are suitable for showing the entire world, others for half of it, and some are only useful over small areas. For more information, see "Projection Distortions" on page 8-2. For a list of available projections, see "Summary and Guide to Projections" on page 8-45. If you want to use a projection that is not included in this list, create a project instead.

Project coordinates by using the projfwd function and unproject coordinates using the projinv function.

Use Inverse Projection to Recover Geographic Coordinates

When geospatial data has plane coordinates (i.e., it comes preprojected, as do many satellite images and municipal map data sets), it is usually possible to recover geographic coordinates if the projection parameters and datum are known. Using this information, you can perform an inverse projection, running the projection backward to solve for latitude and longitude. The toolbox can perform accurate inverse projections for any of its projection functions as long as the original projection parameters and reference ellipsoid (or spherical radius) are provided to it.

Note Converting a position given in latitude-longitude to its equivalent in a projected map coordinate system involves converting from units of angle to units of length. Likewise, unprojecting a point position changes its units from those of length to those of angle). Unit conversion functions such as deg2km and km2deg also convert coordinates between angles and lengths, but do not transform the space they inhabit. You cannot use them to project or unproject coordinate data.

Projection Distortions

All map projections introduce distortions compared to maps on globes. Distortions are inherent in flattening the sphere, and can take several forms:

- Areas Relative size of objects (such as continents)
- Directions Azimuths (angles between points and the poles)
- Distances Relative separations of points (such as a set of cities)
- Shapes Relative lengths and angles of intersection

Some classes of map projections maintain areas, and others preserve local shapes, distances, or directions. No projection, however, can preserve all these characteristics. Choosing a projection thus always requires compromising accuracy in some way, and that is one reason why so many different map projections have been developed. For any given projection, however, the smaller the area being mapped, the less distortion it introduces if properly centered. Mapping Toolbox tools help you to quantify and visualize projection distortions.

References

- [1] Snyder, J. P. "Map Projections A working manual." *U.S. Geological Survey Professional Paper* 1395. Washington, D.C.: U.S. Government Printing Office, 1987. doi:10.3133/pp1395
- [2] Maling, D. H. Coordinate Systems and Map Projections. 2nd ed. New York: Pergamon Press, 1992.
- [3] Snyder, J. P., and P. M. Voxland. "An album of map projections." *U.S. Geological Survey Professional Paper 1453*. Washington, D.C.; U.S. Government Printing Office, 1989. doi:10.3133/pp1453
- [4] Snyder, J. P. Flattening the Earth 2000 Years of Map Projections. Chicago, IL: University of Chicago Press, 1993.

See Also

More About

- "Quantitative Properties of Map Projections" on page 8-4
- "Projection Parameters" on page 8-16

Quantitative Properties of Map Projections

A sphere, unlike a polyhedron, cone, or cylinder, cannot be reformed into a plane. In order to portray the surface of a round body on a two-dimensional flat plane, you must first define a *developable surface* (i.e., one that can be *cut* and *flattened* onto a plane without stretching or creasing) and devise rules for systematically representing all or part of the spherical surface on the plane. Any such process inevitably leads to distortions of one kind or another. Five essential characteristic properties of map projections are subject to distortion: *shape*, *distance*, *direction*, *scale*, and *area*. No projection can retain more than one of these properties over a large portion of the Earth. This is not because a sufficiently clever projection has yet to be devised; the task is physically impossible. The technical meanings of these terms are described below.

• Shape (also called *conformality*)

Shape is preserved locally (within "small" areas) when the scale of a map at any point on the map is the same in any direction. Projections with this property are called conformal. In them, meridians (lines of longitude) and parallels (lines of latitude) intersect at right angles. An older term for conformal is *orthomorphic* (from the Greek *orthos*, straight, and *morphe*, shape).

• Distance (also called *equidistance*)

A map projection can preserve distances from the center of the projection to all other places on the map (but from the center only). Such a map projection is called *equidistant*. Maps are also described as equidistant when the separation between parallels is uniform (e.g., distances along meridians are maintained). No map projection maintains distance proportionality in all directions from any arbitrary point.

Direction

A map projection preserves direction when azimuths (angles from the central point or from a point on a line to another point) are portrayed correctly in all directions. Many azimuthal projections have this property.

• Scale

Scale is the ratio between a distance portrayed on a map and the same extent on the Earth. No projection faithfully maintains constant scale over large areas, but some are able to limit scale variation to one or two percent.

• Area (also called equivalence)

A map can portray areas across it in proportional relationship to the areas on the Earth that they represent. Such a map projection is called equal-area or equivalent. Two older terms for equal-area are *homolographic* or *homalographic* (from the Greek *homalos* or *homos*, same, and *graphos*, write), and *authalic* (from the Greek *autos*, same, and *ailos*, area), and *equireal*. Note that no map can be both equal-area and conformal.

For a complete description of the properties that specific map projections maintain, see "Summary and Guide to Projections" on page 8-45.

The Three Main Families of Map Projections

In this section...

"Unwrapping the Sphere to a Plane" on page 8-5

"Cylindrical Projections" on page 8-5

"Conic Projections" on page 8-6

"Azimuthal Projections" on page 8-7


Unwrapping the Sphere to a Plane


Mapmakers have developed hundreds of map projections, over several thousand years. Three large families of map projection, plus several smaller ones, are generally acknowledged. These are based on the types of geometric shapes that are used to transfer features from a sphere or spheroid to a plane. Map projections are based on *developable surfaces*, and the three traditional families consist of cylinders, cones, and planes. They are used to classify the majority of projections, including some that are not analytically (geometrically) constructed. In addition, a number of map projections are based on polyhedra. While polyhedral projections have interesting and useful properties, they are not described in this guide.

Which developable surface to use for a projection depends on what region is to be mapped, its geographical extent, and the geometric properties that areas, boundaries, and routes need to have, given the purpose of the map. The following sections describe and illustrate how the cylindrical, conic, and azimuthal families of map projections are constructed and provides some examples of projections that are based on them.

Cylindrical Projections

A *cylindrical* projection is produced by wrapping a cylinder around a globe representing the Earth. The map projection is the image of the globe projected onto the cylindrical surface, which is then unwrapped into a flat surface. When the cylinder aligns with the polar axis, parallels appear as horizontal lines and meridians as vertical lines. Cylindrical projections can be either equal-area, conformal, or equidistant. The following figure shows a regular cylindrical or *normal aspect* orientation in which the cylinder is tangent to the Earth along the Equator and the projection radiates horizontally from the axis of rotation. The projection method is diagrammed on the left, and an example is given on the right (equal-area cylindrical projection, normal/equatorial aspect).





For a description of projection aspect, see "Projection Aspect" on page 8-9.

Some widely used cylindrical map projections are

- · Equal-area cylindrical projection
- Equidistant cylindrical projection
- Mercator projection
- · Miller projection
- Plate Carrée projection
- Universal transverse Mercator projection

Pseudocylindrical Map Projections


All cylindrical projections fill a rectangular plane. *Pseudocylindrical* projection outlines tend to be barrel-shaped rather than rectangular. However, they do resemble cylindrical projections, with straight and parallel latitude lines, and can have equally spaced meridians, but meridians are curves, not straight lines. Pseudocylindrical projections can be equal-area, but are not conformal or equidistant.

Some widely-used pseudocylindrical map projections are

- Eckert projections (I-VI)
- · Goode homolosine projection
- Mollweide projection
- · Quartic authalic projection
- Robinson projection
- Sinusoidal projection

Conic Projections

A *conic* projection is derived from the projection of the globe onto a cone placed over it. For the *normal aspect*, the apex of the cone lies on the polar axis of the Earth. If the cone touches the Earth at just one particular parallel of latitude, it is called *tangent*. If made smaller, the cone will intersect the Earth twice, in which case it is called *secant*. Conic projections often achieve less distortion at mid- and high latitudes than cylindrical projections. A further elaboration is the *polyconic* projection, which deploys a family of tangent or secant cones to bracket a succession of bands of parallels to yield even less scale distortion. The following figure illustrates conic projection, diagramming its construction on the left, with an example on the right (Albers equal-area projection, polar aspect).





Some widely-used conic projections are

- · Albers Equal-area projection
- Equidistant projection
- · Lambert conformal projection
- Polyconic projection

Azimuthal Projections

An *azimuthal* projection is a projection of the globe onto a plane. In polar aspect, an azimuthal projection maps to a plane tangent to the Earth at one of the poles, with meridians projected as straight lines radiating from the pole, and parallels shown as complete circles centered at the pole. Azimuthal projections (especially the orthographic) can have equatorial or oblique aspects. The projection is centered on a point, that is either on the surface, at the center of the Earth, at the antipode, some distance beyond the Earth, or at infinity. Most azimuthal projections are not suitable for displaying the entire Earth in one view, but give a sense of the globe. The following figure illustrates azimuthal projection, diagramming it on the left, with an example on the right (orthographic projection, polar aspect).





Some widely used azimuthal projections are

- Equidistant azimuthal projection
- Gnomonic projection
- Lambert equal-area azimuthal projection
- Orthographic projection
- Stereographic projection
- Universal polar stereographic projection

Projection Aspect

A map projection's *aspect* is its orientation on the page or display screen. If north or south is straight up, the aspect is said to be *equatorial*; for most projections this is the *normal* aspect. When the central axis of the developable surface is oriented east-west, the projection's aspect is *transverse*. Projections centered on the North Pole or the South Pole have a *polar* aspect, regardless of what meridian is up. All other orientations have an *oblique* aspect. So far, the examples and discussions of map displays have focused on the *normal* aspect, by far the most commonly used. This section discusses the use of *transverse*, *oblique*, and *skew-oblique* aspects. For an example, see "Control the Map Projection Aspect with an Orientation Vector" on page 8-11.

Projection aspect is primarily of interest in the display of maps. However, this section also discusses how the idea of projection aspect as a coordinate system transformation can be applied to map variables for analytical purposes.

Note The projection aspect discussed in this section is different from the Aspect property of axesm-based maps. The Aspect property of axesm-based maps controls the orientation of the figure axes. For instance, if a map is in a normal setting with a *landscape* orientation, a switch to a transverse aspect rotates the axes by 90°, resulting in a *portrait* orientation. To display a map in the transverse aspect, combine the transverse aspect property with a -90° skew angle. The skew angle is the last element of the Origin parameter. For example, a [0 0 -90] vector would produce a transverse map.


The Orientation Vector

The Origin property of axesm-based maps is a vector describing the geometry of the displayed projection. This property is called an *orientation vector* (prior versions called it the *origin vector*). The vector takes this form:

orientvec = [latitude longitude orientation]

The latitude and longitude represent the geographic coordinates of the center point of the display from which the projection is calculated. The orientation refers to the clockwise angle from *straight up* at which the North Pole points from this center point. The default orientation vector is $[0\ 0\ 0]$; that is, the projection is centered on the geographic point $(0^{\circ},0^{\circ})$ and the North Pole is *straight up* from this point. Such a display is in a *normal* aspect. Changes to only the longitude value of the orientation vector do not change the aspect; thus, a normal aspect is one centered on the Equator in latitude with an orientation of 0° .


Both of these Miller projections have normal aspects, despite having different orientation vectors:



This makes sense if you think about a simple, true cylindrical projection. This is the projection of the globe onto a cylinder wrapped around it. For normal aspects, this cylinder is tangent to the globe at the Equator, and changing the origin longitude simply corresponds to rotating the sphere about the longitudinal axis of the cylinder. If you continue with the wrapped-cylinder model, you can understand the other aspects as well.

Following this description, a *transverse* projection can be thought of as a cylinder wrapped around the globe tangent at the poles and along a meridian and its antipodal meridian. Finally, when such a cylinder is tangent along any great circle other than a meridian, the result is an *oblique* projection.

Here are diagrams of the four cylindrical map orientations, or aspects:



Of course, few projections are true cylindrical projections, but the concept of the wrapped cylinder is nonetheless a convenient way to describe aspect.


For an example that uses the orientation vector, see "Control the Map Projection Aspect with an Orientation Vector" on page 8-11.

Control the Map Projection Aspect with an Orientation Vector

The best way to gain an understanding of projection aspect is to experiment with orientation vectors. The following example uses a pseudocylindrical projection, the sinusoidal.

Create a default axesm-based map in a sinusoidal projection, turn on the graticule, and display the coast data set as filled polygons. The continents and graticule appear in *normal* aspect.

```
figure
axesm sinusoid
framem on
gridm on
tightmap tight
load coastlines
patchm(coastlat,coastlon,'g')
title('Normal aspect: orientation vector = [0 0 0]')
```




Inspect the orientation vector from the axesm-based map. By default, the origin is set at (0°E, 0°N), oriented 0° from vertical.

```
getm(gca,'Origin')
ans = 1 \times 3
      0
```

In the normal aspect, the North Pole is at the top of the image. To create a *transverse* aspect, imagine pulling the North Pole down to the center of the display, which was originally occupied by the point (0°,0°). Do this by setting the first element of Origin parameter to a latitude of 90°N. The shape of the frame is unaffected. This is still a sinusoidal projection.


```
setm(gca, 'Origin', [90 0 0])
title('Transverse aspect: orientation vector = [90 0 0]')
```



Transverse aspect: orientation vector = [90 0 0]


The normal and transverse aspects can be thought of as limiting conditions. Anything else is an oblique aspect. Conceptually, if you push the North Pole halfway back to its original position, that is, to the position originally occupied by the point (45°N, 0°E) in the normal aspect, the result is a simple oblique aspect. You can think of this as pulling the new origin (45°N, 0°) to the center of the image, the place that (0°,0°) occupied in the normal aspect.

```
setm(gca,'Origin',[45 0 0])
title('Oblique aspect: orientation vector = [45 0 0]')
```



The previous examples of projection aspect kept the aspect orientation at 0° . If you alter the orientation, an oblique aspect becomes a *skew-oblique* orientation. Imagine the previous example with an orientation of 45° . Think of this as pulling the new origin $(45^{\circ}\text{N},0^{\circ}\text{E})$, down to the center of the projection and then rotating the projection until the North Pole lies at an angle of 45° clockwise from straight up with respect to the new origin. As in the previous example, the location $(45^{\circ}\text{N},0^{\circ}\text{E})$ still occupies the center of the map.

```
setm(gca,'Origin',[45 0 45])
title('Skew-Oblique aspect: orientation vector = [45 0 45]')
```



The base projection can be thought of as a standard coordinate system, and the normal aspect conforms to it. The features of a projection are maintained in any aspect, *relative to the base projection*. As the preceding illustrations show, the outline (frame) does not change. Nondirectional projection characteristics also do not change. For example, the sinusoidal projection is equal-area, no matter what its aspect. Directional characteristics must be considered carefully, however. In the normal aspect of the sinusoidal projection, scale is true along every parallel and the central meridian. This is not the case for the skew-oblique aspect; however, scale is true along the paths of the transformed parallels and meridian.

Any projection can be viewed in alternate aspects and this can often be quite useful. For example, the transverse aspect of the Mercator projection is widely used in cartography, especially for mapping regions with predominantly north-south extent. One candidate for such handling might be Chile. Oblique Mercator projections might be used to map long regions that run neither north and south nor east and west, such as New Zealand.

Projection Parameters

Every projection has at least one parameter that controls how it transforms geographic coordinates into planar coordinates. Some projections are rather fixed, and aside from the orientation vector and nominal scale factor, have no parameters that the user should vary, as to do so would violate the definition of the projection. For example, the Robinson projection has one standard parallel that is fixed by definition at 38° North and South; the Cassini and Wetch projections cannot be constructed in other than Normal aspect. In general, however, projections have several variable parameters. The following section discusses map projection parameters and provides guidance for setting them.

Projection Characteristics Maps Can Have

In addition to the name of the projection itself, the parameters that a map projection can have are

- *Aspect* Orientation of the projection on the display surface
- *Center* or *Origin* Latitude and longitude of the midpoint of the display
- Scale Factor Ratio of distance on the map to distance on the ground
- *Standard Parallel(s)* Chosen latitude(s) where scale distortion is zero
- False Northing Planar offset for coordinates on the vertical map axis
- False Easting Planar offset for coordinates on the horizontal map axis
- Zone Designated latitude-longitude quadrangle used to systematically partition the planet for certain classes of projections

While not all projections require all these parameters, there will always be a projection aspect, origin, and scale.

Other parameters are associated with the graphic expression of a projection, but do not define its mathematical outcome. These include

- · Map latitude and longitude limits
- · Frame latitude and longitude limits

However, as certain projections are unable to map an entire planet, or become very distorted over large regions, these limits are sometimes a necessary part of setting up a projection.


Determining Projection Parameters

In the following exercise, you define an <code>axesm</code>-based map and examine default parameters for a cylindrical, a conic, and an azimuthal projection.

Set up a default Mercator projection (which is cylindrical) and pass its handle to the getm function to query projection parameters:

```
figure;
h=axesm('Mapprojection','mercator','Grid','on','Frame','on',...
'MlabelParallel',0,'PlabelMeridian',0,'mlabellocation',60,...
'meridianlabel','on','parallellabel','on')
```

The graticule and frame for the default map projection are shown below.



Query the handle of the axesm-based map using getm to inspect the properties that pertain to map projection parameters. The principal ones are aspect, origin, scalefactor, nparallels, mapparallels, falsenorthing, falseeasting, zone, maplatlimit, maplonlimit, rlatlimit, and flonlimit:

```
getm(h,'aspect')
ans =
     normal
getm(h,'origin')
ans =
           0
                 0
     0
getm(h,'scalefactor')
ans =
getm(h,'nparallels')
ans =
     1
getm(h,'mapparallels')
ans =
getm(h,'falsenorthing')
ans =
```

```
0
getm(h,'falseeasting')
ans =
     0
getm(h,'zone')
ans =
     []
getm(h,'maplatlimit')
ans =
          86
   -86
getm(h,'maplonlimit')
ans =
  - 180
         180
getm(h,'Flatlimit')
ans =
   -86
          86
getm(h,'Flonlimit')
ans =
         180
  - 180
```


For more information on these and other properties of axesm-based maps, see axesm-Based Map Properties.

Reset the projection type to equal-area conic ('eqaconic'). The figure is redrawn to reflect the change. Determine the parameters that the toolbox changes in response:

```
setm(h,'Mapprojection', 'eqaconic')
getm(h,'aspect')
ans =
    normal
getm(h,'origin')
ans =
    0    0    0
getm(h,'scalefactor')
ans =
    1
getm(h,'nparallels')
ans =
    2
```

```
getm(h,'mapparallels')
ans =
    15
          75
getm(h,'falsenorthing')
ans =
getm(h,'falseeasting')
ans =
getm(h,'zone')
ans =
     []
getm(h,'maplatlimit')
ans =
          86
   -86
getm(h,'maplonlimit')
ans =
  -135
         135
getm(h,'Flatlimit')
ans =
   -86
          86
getm(h,'Flonlimit')
ans =
  - 135
         135
```


The eqaconic projection has two standard parallels, at 15° and 75°. It also has reduced longitude limits (covering 270° rather than 360°). The resulting eqaconic graticule is shown below.



4 Now set the projection type to Stereographic ('stereo') and examine the same properties as you did for the previous projections:

```
setm(h,'Mapprojection','stereo')
setm(gca,'MLabelParallel',0,'PLabelMeridian',0)
getm(h,'aspect')
ans =
normal
getm(h,'origin')
ans =
           0
getm(h,'scalefactor')
ans =
getm(h,'nparallels')
ans =
getm(h,'mapparallels')
ans =
     []
getm(h,'falsenorthing')
ans =
getm(h,'falseeasting')
ans =
getm(h,'zone')
ans =
     []
getm(h,'maplatlimit')
ans =
   -90
          90
getm(h,'maplonlimit')
ans =
  - 180
         180
getm(h,'Flatlimit')
ans =
   -Inf
           90
getm(h,'Flonlimit')
```

The stereographic projection, being azimuthal, does not have standard parallels, so none are indicated. The map limits do not change from the previous projection. The map figure is shown below.



Visualize Spatial Error Using Tissot Indicatrices


A standard method of visualizing the distortions introduced by the map projection is to display small circles at regular intervals across the globe. After projection, the small circles appear as ellipses of various sizes, elongations, and orientations. The sizes and shapes of the ellipses reflect the projection distortions. Conformal projections have circular ellipses, while equal-area projections have ellipses of the same area. This method was invented by Nicolas Tissot in the 19th century, and the ellipses are called *Tissot indicatrices* in his honor. The measure is a tensor function of location that varies from place to place, and reflects the fact that, unless a map is conformal, map scale is different in every direction at a location.

Visualize Projection Distortions Using Tissot Indicatrices

This example shows how to add Tissot indicatrices to a map display.


Set up a Sinusoidal projection in a skewed aspect, plotting the graticule.

```
figure
axesm sinusoid
gridm on
framem on
setm(gca,'Origin',[20 30 45])
```




Load the coast data set and plot it as green patches.

load coastlines
patchm(coastlat,coastlon,'g')




Plot the default Tissot diagram. Notice that the circles vary considerably in shape. This indicates that the Sinusoidal projection is not conformal. Despite the distortions, however the circles all cover equal amounts of area on the map because the projection has the equal-area property. Default Tissot diagrams are drawn with blue unfilled 100-point circles spaced 30 degrees apart in both directions. The default circle radius is 1/10 of the current radius of the reference ellipsoid (by default that radius is 1).

tissot



Clear the Tissot diagram, rotate the projection to a polar aspect, and plot a new Tissot diagram using circles paced 20 degrees apart, half as big as before, drawn with 20 points, and drawn in red. In the result, note that the circles are drawn faster because fewer points are computed for each one. Also note that the distortions are still smallest close to the map origin, and still greatest near the map frame.

```
clmo tissot
setm(gca,'Origin',[90 0 45])
tissot([20 20 .05 20],'Color','r')
```



See Also

distortcalc | mdistort | tissot

More About

• "Quantitative Properties of Map Projections" on page 8-4

Quantify Map Distortions at Point Locations

The tissot and mdistort functions provide synoptic visual overviews of different forms of map projection error. Sometimes, however, you need numerical estimates of error at specific locations in order to quantify or correct for map distortions. This is useful, for example, if you are sampling environmental data on a uniform basis across a map, and want to know precisely how much area is associated with each sample point, a statistic that will vary by location and be projection dependent. Once you have this information, you can adjust environmental density and other statistics you collect for areal variations induced by the map projection.

A Mapping Toolbox function returns location-specific map error statistics from the current projection or an mstruct. The distortcalc function computes the same distortion statistics as mdistort does, but for specified locations provided as arguments. You provide the latitude-longitude locations one at a time or in vectors. The general form is

```
[areascale,angdef,maxscale,minscale,merscale,parscale] = ...
distortcalc(mstruct,lat,long)
```

However, if you are evaluating the current map figure, omit the mstruct. You need not specify any return values following the last one of interest to you.

Use distortcalc to Determine Map Projection Geometric Distortions

The following exercise uses distortcalc to compute the maximum area distortion for a map of Argentina from the land areas data set.

1 Read the North and South America polygon:

```
Americas = shaperead('landareas.shp','UseGeoCoords',true, ...
'Selector', {@(name) ...
strcmpi(name,{'north and south america'}),'Name'});
```


2 Set the spatial extent (map limits) to contain the southern part of South America and also include an area closer to the South Pole:

```
mlatlim = [-72.0 -20.0];
mlonlim = [-75.0 -50.0];
[alat, alon] = maptriml([Americas.Lat], ...
        [Americas.Lon], mlatlim, mlonlim);
```

3 Create a Mercator cylindrical conformal projection using these limits, specify a five-degree graticule, and then plot the outline for reference:

```
figure;
axesm('MapProjection','mercator','grid','on', ...
    'MapLatLimit',mlatlim,'MapLonLimit',mlonlim,...
    'MLineLocation',5, 'PLineLocation',5)
plotm(alat,alon,'b')
```

The map looks like this:



4 Sample every tenth point of the patch outline for analysis:

```
alats = alat(1:10:numel(alat));
alons = alon(1:10:numel(alat));
```

5 Compute the area distortions (the first value returned by distortcalc) at the sample points:

```
adistort = distortcalc(alats, alons);
```

6 Find the range of area distortion across Argentina (percent of a unit area on, in this case, the equator):


```
adistortmm = [min(adistort) max(adistort)]
adistortmm =
    1.1790    2.7716
```

As Argentina occupies mid southern latitudes, its area on a Mercator map is overstated, and the errors vary noticeably from north to south.

Remove any NaNs from the coordinate arrays and plot symbols to represent the relative distortions as proportional circles, using scatterm:

```
nanIndex = isnan(adistort);
alats(nanIndex) = [];
alons(nanIndex) = [];
adistort(nanIndex) = [];
scatterm(alats,alons,20*adistort,'red','filled')
```

The resulting map is shown below:



The degree of area overstatement would be considerably larger if it extended farther toward the pole. To see how much larger, get the area distortion for 50°S, 60°S, and 70°S:

Note You can only use distortcalc to query locations that are within the current map frame or mstruct limits. Outside points yield NaN as a result.

9 Using this technique, you can write a simple script that lets you query a map repeatedly to determine distortion at any desired location. You can select locations with the graphic cursor using inputm. For example,

```
>> a=distortcalc(plat,plon)
a =
4.6048
```

Naturally the answer you get will vary depending on what point you pick. Using this technique, you can write a simple script that lets you query a map repeatedly to determine any distortion statistic at any desired location.

Try changing the map projection or even the orientation vector to see how the choice of projection affects map distortion. For further information, see the reference page for distortcalc.

Rotational Transformations on the Globe

In "The Orientation Vector" on page 8-9, you explored the concept of altering the aspect of a map projection in terms of pushing the North Pole to new locations. Another way to think about this is to redefine the coordinate system, and then to compute a normal aspect projection based on the new system. For example, you might redefine a spherical coordinate system so that your home town occupies the origin. If you calculated a map projection in a normal aspect with respect to this *transformed* coordinate system, the resulting display would look like an oblique aspect of the *true* coordinate system of latitudes and longitudes.

This transformation of coordinate systems can be useful independent of map displays. If you transform the coordinate system so that your home town is the new *North Pole*, then the transformed coordinates of all other points will provide interesting information.

Note The types of coordinate transformations described here are appropriate for the spherical case only. Attempts to perform them on an ellipsoid will produce incorrect answers on the order of several to tens of meters.

When you place your home town at a pole, the spherical distance of each point from your hometown becomes 90° minus its transformed latitude (also known as a *colatitude*). The point antipodal to your town would become the *South Pole*, at -90°. Its distance from your hometown is 90°-(-90°), or 180°, as expected. Points 90° distant from your hometown all have a transformed latitude of 0°, and thus make up the transformed *equator*. Transformed longitudes correspond to their respective great circle azimuths from your home town.

Reorient Vector Data with rotatem

The rotatem function uses an orientation vector to transform latitudes and longitudes into a new coordinate system. The orientation vector can be produced by the newpole or putpole functions, or can be specified manually.

As an example of transforming a coordinate system, suppose you live in Midland, Texas, at (32°N,102°W). You have a brother in Tulsa (36.2°N,96°W) and a sister in New Orleans (30°N,90°W).

1 Define the three locations:

```
midl_lat = 32;  midl_lon = -102;
tuls_lat = 36.2; tuls_lon = -96;
newo lat = 30;  newo lon = -90;
```

2 Use the distance function to determine great circle distances and azimuths of Tulsa and New Orleans from Midland:

```
newo_lat,newo_lon)
```

Tulsa is about 6.5 degrees distant, New Orleans about 10.5 degrees distant.

3 Compute the absolute difference in azimuth, a fact you will use later.

```
azdif = abs(az2tuls-az2neworl)
azdif =
   49.7258
```

dist2neworl = 10.4727

az2neworl = 97.8644

Today, you feel on top of the world, so make Midland, Texas, the *north pole* of a transformed coordinate system. To do this, first determine the origin required to put Midland at the pole using newpole:

```
origin = newpole(midl_lat,midl_lon)
origin =
    58    78    0
```

The origin of the new coordinate system is (58°N, 78°E). Midland is now at a new latitude of 90°.

5 Determine the transformed coordinates of Tulsa and New Orleans using the rotatem command. Because its units default to radians, be sure to include the degrees keyword:

6 Show that the new colatitudes of Tulsa and New Orleans equal their distances from Midland computed in step 2 above:

```
tuls_colat1 = 90-tuls_lat1
tuls_colat1 =
   6.5032
newo_colat1 = 90-newo_lat1
newo_colat1 =
   10.4727
```

7 Recall from step 4 that the absolute difference in the azimuths of the two cities from Midland was 49.7258°. Verify that this equals the difference in their new longitudes:

```
tuls_lon1-newo_lon1
ans =
    49.7258
```

You might note small numerical differences in the results (on the order of 10^{-6}), due to round-off error and trigonometric functions.

For further information, see the reference pages for rotatem, newpole, putpole, neworig, and org2pol.

Reorient Gridded Data


This example shows how to transform a regular data grid into a new one with its data rearranged to correspond to a new coordinate system using the <code>neworig</code> function. You can transform coordinate systems of data grids as well as vector data. When regular data grids are manipulated in this manner, distance and azimuth calculations with the map variable become row and column operations.

Load elevation raster data and a geographic cells reference object. Transform the data set to a new coordinate system in which a point in Sri Lanka is the north pole. Reorient the data grid by using the neworig function. Note that the result, [Z,lat,lon], is a geolocated data grid, not a regular data grid like the original data.

```
load topo60c
origin = newpole(7,80);
[Z,lat,lon] = neworig(topo60c,topo60cR,origin);
```

Display the new map, in normal aspect, as its orientation vector shows. Note that every cell in the first row of the new grid is 0 to 1 degrees distant from the point new origin. Every cell in its second row is 1 to 2 degrees distant, and so on. In addition, every cell in a particular column has the same great circle azimuth from the new origin.

```
axesm miller
lat = linspace(-90,90,90);
lon = linspace(-180,180,180);
surfm(lat,lon,Z);
demcmap(topo60c)
```



```
mstruct = getm(gca);
mstruct.origin

ans = 1×3
0 0 0
```

Create a UTM Map

The Universal Transverse Mercator (UTM) system divides the world into a regular, nonoverlapping grid of quadrangles called *zones*. Each zone is 8-by-6 degrees in extent and uses a transverse Mercator projection that is designed to limit distortion. UTM zones are identified using a grid reference in the form of a number followed by a letter, for example 31T. Each UTM zone has a false northing and a false easting. These are offsets that enable each zone to have positive coordinates in both directions. All UTM zones have a false easting of 500,000 meters. All zones in the northern hemisphere have a false northing of 0 meters, and all zones in the southern hemisphere have a false northing of 10,000,000 meters.

The UTM system is defined between 80 degrees south and 84 degrees north. Beyond these limits, use the Universal Polar Stereographic (UPS) system instead. The UPS system has two zones, north and south. Both UPS zones have a false northing and false easting of 2,000,000 m.

Create a UTM Map

You can create UTM maps with the axesm function. However, unlike other projections, the map frame is limited to an 8-by-6 degree map window (the UTM zone).

Create a UTM axesm-based map.


axesm utm

Get the properties of the axesm-based map and inspect them in the Command Window or with the Variables editor. Note that the default zone is 31N. This is selected because the map origin defaults to $[0\ 3\ 0]$, which is on the equator and at a longitude of 3° E. This is the center longitude of zone 31N, which has a latitude limit of $[0\ 8]$, and a longitude limit of $[0\ 6]$.


```
h = getm(gca);
h.zone
ans =
'31N'
```

Change the zone to 32N, one zone to the east of the default, and inspect the other parameters again. Note that the map origin and limits are adjusted for zone 32N.

```
setm(gca,'zone','32n')
```




```
h = getm(gca);
Draw the map grid and label it.
setm(gca,'grid','on','meridianlabel','on','parallellabel','on')
```



Load and plot the coastline data set to see a close-up of the Gulf of Guinea and Bioko Island in UTM.

load coastlines
plotm(coastlat,coastlon)



See Also utm | ups

Set UTM Parameters Interactively

The easiest way to use the UTM projection is through a graphical user interface. You can create or modify a UTM area of interest with the axesmui projection control panel, and get further assistance form the utmzoneui control panel.


You can **Shift**+click in the window of an axesm-based map, or type axesmui to display the projection control panel. Here you start from scratch:

figure axesm utm axesmui

The Map Projection field is set to cyln: Universal Transverse Mercator (UTM).

Note For UTM and UPS maps, the **Aspect** field is set to **normal** and cannot be changed. If you attempt to specify transverse, an error results.

2 Click the **Zone** button to open the utmzoneui panel. Click the map near your area of interest to pick the zone:




Note that while you can open the utmzoneui control panel from the command line, you then have to manually update the figure with the zone name it returns with a setm command:

setm(gca,'zone',ans)

3 Click the **Accept** button.

The utmzoneui panel closes, and the zone field is set to the one you picked. The map limits are updated accordingly, and the geoid parameters are automatically set to an appropriate ellipsoid




definition for that zone. You can override the default choice by selecting another ellipsoid from the list or by typing the parameters in the **Geoid** field.

4 Click **Apply** to close the projection control panel.

The projection is then ready for projection calculations or map display commands.

Now view a choropleth base map from the usstatehi shapefile for the area within the zone that you just selected:



What you see depends on the zone you selected. The preceding display is for zone 18T, which contains portions of New England and the Middle Atlantic states.

You can also calculate projected UTM grid coordinates from latitudes and longitudes:

Work in UTM Without a Displayed Map

You can set up UTM to calculate coordinates without generating a map display, using the defaultm function. The utmzone and utmgeoid functions help you select a zone and an appropriate ellipsoid. In this example, you generate UTM coordinate data for a location in New York City, using that point to define the projection itself.

Define a location in New York City. Obtain the UTM zone for this point.

```
lat = 40.7;
lon = -74.0;
z = utmzone(lat,lon)
z =
'18T'
```

Get the suggested ellipsoid vector and name for this zone.

```
[ellipsoid,estr] = utmgeoid(z)
ellipsoid = 1×2
10<sup>6</sup> ×
     6.3782     0.0000
estr =
'clarke66'
```

Set up the UTM coordinate system based on this information.

```
utmstruct = defaultm('utm');
utmstruct.zone = z;
utmstruct.geoid = ellipsoid;
utmstruct = defaultm(utmstruct);
```

Transform the coordinates, without a map display.

```
[x,y] = projfwd(utmstruct,lat,lon)

x = 5.8448e+05

y = 4.5057e+06
```

Compute the zone limits (latitude and longitude limits) for a specified zone by using the utmzone function. You can also call utmzone recursively to obtain the limits of the UTM zone within which a point location falls.

```
zonelats = 1 \times 2
     40
             48
zonelons = 1 \times 2
    -78
          -72
```

Alternatively, set up a UTM coordinate system using a projers object. To create the object, specify an EPSG code. For information about EPSG codes, see the EPSG registry. Verify that the projers object has the correct name and ellipsoid. Then, transform the coordinates.

```
p = projcrs(26718);
p.Name
ans =
"NAD27 / UTM zone 18N"
p.GeographicCRS.Spheroid.Name
ans =
'Clarke 1866'
[xp,yp] = projfwd(p,lat,lon)
xp = 5.8448e + 05
yp = 4.5057e + 06
```


See Also

projcrs | utmgeoid | utmzone | projfwd | defaultm

Use the Transverse Aspect to Map Across UTM Zones

To display areas that extend across more than one UTM zone, use the Mercator projection in a transverse aspect. UTM is a zone-based coordinate system and is designed to be used like a map series, selecting from the appropriate sheet. While it is possible to extend one zone's coordinates into a neighboring zone's territory, this is not normally done. This example shows a transverse Mercator projection appropriate to Chile. In the example, note how the projection's line of zero distortion is aligned with the predominantly north-south axis of the country. Of course, you do not obtain coordinates in meters that would match those of a UTM projection, but the results will be nearly as accurate. To place the zero distortion line exactly on the midline of the country, use better estimates of the orientation vector's central meridian and orientation angle.

Set up an axesm-based map with a transverse aspect and display a map of Chile. Calculate the map distortion.



You might receive warnings about points from landareas.shp falling outside the valid projection region. You can ignore such warnings.

Summary and Guide to Projections

Use projections to display latitude-longitude coordinate data on maps. Choose a projection method by considering these criteria:

- Family Choose a cylindrical, conic, or azimuthal projection based on your purpose and region of interest. For more information, see "The Three Main Families of Map Projections" on page 8-5.
- Properties Choose a projection based on the properties you want to preserve, such as shape, distance, direction, scale, and area. For more information, see "Quantitative Properties of Map Projections" on page 8-4.
- Distortion Choose a projection based on the distortion you want to minimize or eliminate. For more information, see "Map Projections and Distortions" on page 8-2.

These tables show the map projections you can use with map projection structures and axesm-based maps. For more information about map projection structures, see defaultm. For more information about axesm-based maps, see axesm.

Note Most projection IDs are also functions on the MATLAB search path. These functions are only used in the implementation of functions such as defaultm and axesm, and therefore their syntaxes are not documented.

Cylindrical Projections

Projection Name	Projection ID	I-	Conf orma I		Special Features	Example
Balthasart	balthsrt	V	X	X		
Behrmann	behrmann	•	X	X	_	
Bolshoi Sovietskii Atlas Mira	bsam	x	x	x	_	

Projection Name	Projection ID	Equa I- Area	orma	Equi dista nt	Special Features	Example
Braun Perspective	braun	х	x	x	_	
Cassini	cassini	X	x	•	_	
Cassini - Standard	cassinistd	X	X	X		
Central	ccylin	X	X	X	_	
Equal-Area Cylindrical	eqacylin	'	X	x	_	
Equidistant Cylindrical	eqdcylin	х	x	V	_	

Projection Name	Projection ID	I-	Conf orma I	Equi dista nt	Special Features	Example
Gall Isographic	giso	х	х	V	_	
Gall Orthographic	gortho	•	х	X		
Gall Stereographic	gstereo	X	х	x		
Lambert Equal-Area Cylindrical	lambcyln	V	Х	X	_	
Mercator	mercator	х	•	X	Rhumb lines are straight.	
Miller	miller	х	х	x	_	

Projection Name	Projection ID	Equa I- Area	orma	Equi dista nt	Special Features	Example
Plate Carrée	pcarree	x	X			
Transverse Mercator	tranmerc	X	V	X	_	
Trystan Edwards	trystan	~	x	x	_	
Universal Transverse Mercator (UTM)	utm	х	~	x	_	_
Wetch	wetch	X	X	X		

Pseudocylindrical Projections

Projection Name	ID		orma		Special Features	Example
Apianus II	apianus	X	X	X	_	

Projection Name	Projection ID	I-	Conf orma I	Equi dista nt	Special Features	Example
Collignon	collig	~	x	х	_	
Craster Parabolic	craster	•	X	X	_	
Eckert I	eckert1	x	X	Х	_	
Eckert II	eckert2	•	X	X	_	
Eckert III	eckert3	x	x	X	_	
Eckert IV	eckert4	•	x	X	_	
Eckert V	eckert5	x	x	X	_	
Eckert VI	eckert6	•	X	х	_	
Fournier	fournier	•	X	Х	_	

Projection Name	Projection ID	Equa - Area	Conf orma I	Equi dista nt	Special Features	Example
Goode Homolosine	goode	V	X	x	_	
Hatano Asymmetrical Equal-Area	hatano	~	Х	x	_	
Kavraisky V	kavrsky5	~	X	x	_	
Kavraisky VI	kavrsky6	~	X	x	_	
Loximuthal	loximuth	Х	х	x	Rhumb lines from the central point are straight, true to scale, and correct in azimuth.	
McBryde-Thomas Flat- Polar Parabolic	flatplrp	~	х	х	_	
McBryde-Thomas Flat- Polar Quartic	flatplrq	V	х	х	_	
McBryde-Thomas Flat- Polar Sinusoidal	flatplrs	~	х	X	_	

Projection Name	Projection ID	I-	Conf orma I	Equi dista nt	Special Features	Example
Mollweide	mollweid	•	X	x	_	
Putnins P5	putnins5	x	X	x	_	
Quartic Authalic	quartic	~	х	x	_	
Robinson	robinson	x	X	X	_	
Sinusoidal	sinusoid	~	X	x	_	
Tissot Modified Sinusoidal	modsine	~	Х	Х	_	
Wagner IV	wagner4	•	Х	x	_	
Winkel 1	winkel	X	х	x	_	

Conic Projections

Projection Name	Projection ID	Equa - Area	orma	Equi dista nt	Special Features	Example
Albers Equal-Area Conic	eqaconic	~	х	х		
Albers Equal-Area Conic – Standard	eqaconicst d	~	х	х	_	
Equidistant Conic	eqdconic	х	х	~		
Equidistant Conic - Standard	eqdconicst d	х	х	~		
Lambert Conformal Conic	lambert	х	~	х	_	

Projection Name	Projection ID	Equa I- Area	Conf orma I	Equi dista nt	Special Features	Example
Lambert Conformal Conic - Standard	lambertstd	X	~	x	_	
Murdoch I Conic	murdoch1	х	х	~	The total area is correct.	
Murdoch III Minimum Error Conic	murdoch3	X	X	V	The total area is correct.	

Pseudoconic Projections

Projection Name	Projection ID	Equa - Area	orma	Equi dista nt	Special Features	Example
Bonne	bonne	V	х	х		

Projection Name	Projection ID		orma		Special Features	Example
Werner	werner	V	X	X	_	

Polyconic Projections

Projection Name	Projection ID	I-	Conf orma I	Equi dista nt	Special Features	Example
Polyconic	polycon	X	X	x		
Polyconic - Standard	polyconstd	X	X	X		
Van Der Grinten I	vgrint1	х	х	X		

Azimuthal Projections

Projection Name	Projection ID	Equa - Area		Equi dista nt	Special Features	Example
Breusing Harmonic Mean	breusing	х	х	x		
Equidistant Azimuthal	eqdazim	х	x	V	_	
Gnomonic	gnomonic	x	x	x	Great circles appear as straight lines.	
Lambert Azimuthal Equal-Area	eqaazim	V	X	X		

Projection Name	Projection ID	I-	Conf orma I	Equi dista nt	Special Features	Example
Orthographic	ortho	х	x	x	_	
Stereographic	stereo	х	~	x	Great and small circles appear as either straight lines or circular arcs.	
Universal Polar Stereographic (UPS)	ups	x	V	X	Great and small circles appear as either straight lines or circular arcs.	_
Vertical Perspective Azimuthal	vperspec	х	x	X	_	

Pseudoazimuthal Projections

	ID	Equa - Area	Conf orma I	Equi dista nt	Special Features	Example
Wiechel	wiechel	•	X	X		

Modified Azimuthal Projections

Projection Name	ID				Special Features	Example
Aitoff	aitoff	X	X	X	_	
Briesemeister	bries	V	x	x	_	
Hammer	hammer	•	X	X	_	

See Also

axesm | geoshow | defaultm

Transform Coordinates to a Different Projected CRS

If you directly compare data sets with different projected coordinate reference systems (CRSs), then the results are inaccurate. Therefore, before comparing data sets, first verify that the CRSs are the same. If different projected CRSs have the same underlying geographic CRS, then you can transform the coordinates from one projected CRS to the other. Once the data sets are referenced to the same projected CRS, you can compare them.

To transform projected x-y coordinates to a different projected CRS, first unproject the x-y coordinates to latitude-longitude coordinates by using the projinv function. Then, project the latitude-longitude coordinates to x-y coordinates in a different projected CRS by using the projfwd function.

For example, import a shapefile containing the x- and y-coordinates of roads in Boston. Also import information about the shapefile as a structure. Find the projected CRS for the coordinates by accessing the CoordinateReferenceSystem field of that structure.

```
s = shaperead('boston_roads.shp');
x1 = [s.X];
y1 = [s.Y];
info = shapeinfo('boston_roads.shp');
p1 = info.CoordinateReferenceSystem;
```

Unproject the *x*-*y* coordinates and return latitude-longitude coordinates.

```
[lat,lon] = projinv(p1,x1,y1);
```

Select a new projected CRS for the target projection. For this example, create a projers object for UTM zone 19N. Verify that both projected CRSs have the same geographic CRS. If the geographic CRSs are different, then the projected coordinates may be inaccurate. You can find the geographic CRS by querying the GeographicCRS property of the projers object.


```
p2 = projcrs(26919);
p2.GeographicCRS.Name
ans =
"NAD83"
p1.GeographicCRS.Name
ans =
"NAD83"
```

Project the latitude-longitude coordinates to x-y coordinates by specifying the project you created.


```
[x2,y2] = projfwd(p2,lat,lon);
```

Compare the original x-y coordinates with the new x-y coordinates by displaying them. Add labels and a title to each figure.

```
figure
mapshow(x1,y1)
xlabel('x (meters)')
ylabel('y (meters)')
title(p1.Name)
```



```
figure
mapshow(x2,y2)
xlabel('x (meters)')
ylabel('y (meters)')
title(p2.Name)
```



The visualizations are similar, but the coordinates displayed along the axis rulers correspond to different projected CRSs.

See Also

projinv|projfwd|geocrs|projcrs|shaperead

More About

• "Project and Display Raster Data" on page 8-61

Project and Display Raster Data

To project or unproject regularly-spaced raster data that is associated with a geographic or map reference object, you must first create a coordinate grid that matches the size of the raster. Use different grid creation functions depending on which way you are projecting. When you project latitude-longitude coordinates to x-y coordinates, create a grid using the geographicGrid function. When you unproject x-y coordinates to latitude-longitude coordinates, create a grid using the worldGrid function.

After transforming the raster data, you can display it on a map using visualization functions such as mapshow and geoshow. Use mapshow for projected x-y coordinates and geoshow for unprojected latitude-longitude coordinates.

Project Raster Data

To project data that is associated with a geographic raster reference object, first create a grid of latitude-longitude coordinates for each point in the raster. Then, project the geographic coordinates to x-y map coordinates.

For example, import elevation raster data as an array and a geographic cells reference object. Get the latitude-longitude coordinates for each point in the raster by using the <code>geographicGrid</code> function.


```
[Z,R] = readgeoraster('n39_w106_3arc_v2.dt1');
[lat,lon] = geographicGrid(R);
```

Now that you have your grid, select a map projection to use when projecting the coordinates. For this example, create a projers object for UTM zone 13 in the northern hemisphere. Then, project the latitude-longitude coordinates to *x-y* coordinates.

```
p = projcrs(32613);
[x,y] = projfwd(p,lat,lon);
```

Display the projected raster as a surface by calling mapshow and specifying the x-y coordinates and elevation array. Add axis labels and apply a colormap appropriate for elevation data.

```
figure
mapshow(x,y,Z,'DisplayType','surface')
xlabel('x (meters)')
ylabel('y (meters)')
demcmap(Z)
```



If the geographic CRS of the latitude-longitude coordinates does not match the geographic CRS of the projected CRS, then the projected coordinates may be inaccurate. You can find the geographic CRS of a projers object or a geographic raster reference object by querying their Geographic CRS properties.

p.GeographicCRS.Name

```
ans = "WGS 84"
```

R.GeographicCRS.Name

```
ans = "WGS 84"
```

The DTED file used in this example is courtesy of the US Geological Survey.

Unproject Raster Data

To unproject data that is associated with a map raster reference object, first create a grid of x-y coordinates for each point in the raster. Then, unproject the x-y map coordinates to geographic coordinates.

For example, import an image of Boston as an array and a map cells reference object. Get information about the map projection as a projers object by querying the ProjectedCRS property of the reference object.

```
[Z,R] = readgeoraster('boston.tif');
p = R.ProjectedCRS;
```

Get the x-y coordinates for each point in the raster by using the worldGrid function.


```
[x,y] = worldGrid(R);
```

Unproject the *x-y* coordinates to latitude-longitude coordinates by using the projinv function and specifying the projers object and coordinate grid.

```
[lat,lon] = projinv(p,x,y);
```

Display the unprojected image by calling geoshow and specifying the latitude-longitude coordinates and image array. By default, geoshow displays coordinates using a Plate Carrée projection. Then, add axis labels.

```
figure
geoshow(lat,lon,Z)
xlabel('Longitude (degrees)')
ylabel('Latitude (degrees)')
```



See Also

Functions

projinv|projfwd|intrinsicToWorld|meshgrid|worldGrid

Objects

MapCellsReference | GeographicCellsReference

Creating Web Map Service Maps

- "Basic WMS Terminology" on page 9-2
- "Basic Workflow for Creating WMS Maps" on page 9-3
- "Add Legend to WMS Map" on page 9-6
- "Read WMS Maps Using Different Coordinate Reference Systems" on page 9-11
- "Modify Your Map Request" on page 9-16
- "Overlay Multiple Layers" on page 9-19
- "Animate Data Layers" on page 9-26
- "Display Animation of Radar Images over GOES Backdrop" on page 9-32
- "Read Quantitative Data from WMS Server" on page 9-34
- "Explore Layers on Same Server" on page 9-43
- "Write WMS Layers to KML File" on page 9-46
- "Search for Layers Outside the WMS Database" on page 9-49
- "Create WMS Maps When Internet Access Is Intermittent" on page 9-51
- "Troubleshoot WMS Servers" on page 9-54
- "Introduction to Web Map Display" on page 9-58
- "Basic Workflow for Displaying Web Maps" on page 9-61
- "Display a Web Map" on page 9-62
- "Select a Base Layer Map" on page 9-63
- "Specify a Custom Base Layer" on page 9-65
- "Specify a WMS Layer as a Base Layer" on page 9-67
- "Add an Overlay Layer to the Map" on page 9-69
- "Add Line, Polygon, and Marker Overlay Layers to Web Maps" on page 9-71
- "Remove Overlay Layers on a Web Map" on page 9-77
- "Navigate a Web Map" on page 9-81
- "Close a Web Map" on page 9-83
- "Annotate a Web Map with Measurement Information" on page 9-84
- "Compositing and Animating Web Map Service (WMS) Meteorological Layers" on page 9-88
- "Troubleshoot Common Problems with Web Maps" on page 9-103

Basic WMS Terminology

- Open Geospatial Consortium, Inc. (OGC) An organization comprising companies, government agencies, and universities that defines specifications for providers of geospatial data and developers of software designed to access that data. The specifications ensure that providers and clients can talk to each other and thus promote the sharing of geospatial data worldwide. You can access the Web Map Server Implementation Specification at the OGC website.
- **Web Map Service** The OGC® defines a Web Map Service (WMS) as an entity that "produces maps of spatially referenced data dynamically from geographic information."
- **WMS server** A server that follows the guidelines of the OGC to render maps and return them to clients.
- **georeferenced** Tied to a specific location on the Earth.
- raster data Data represented as a matrix in which each element corresponds to a specific rectangular or quadrangular geographic area.
- map The OGC defines a map as "a portrayal of geographic information as a digital image file suitable for display on a computer screen."
- **raster map** Geographically referenced information stored as a regular array of cells.
- layer A data set containing a specific type of geographic information. Information can include temperature, elevation, weather, orthoimagery, boundaries, demographics, topography, transportation, environmental measurements, or various data from satellites.
- **capabilities document** An XML document containing metadata describing the geographic content offered by a server.

See Also

More About

• "Basic Workflow for Creating WMS Maps" on page 9-3

Basic Workflow for Creating WMS Maps

A Web Map Service (WMS) provides images of publicly accessible geospatial information from webbased sources. This example shows how to find and display a WMS map of satellite imagery for a region around Europe.

Search WMS Database

A layer is a data set that contains a specific type of geographic information, such as elevation, weather, or orthoimagery. Mapping Toolbox $^{\text{TM}}$ contains a database, called the *WMS Database*, that includes more than 100,000 layers from more than 1000 servers. You can search the WMS Database by using the wmsfind function. By default, the wmsfind function searches the WMS Database for matching layer names and layer titles.

For this example, search the WMS Database for layers that mention **eox**. For more information about EOX::Maps, see EOX::Maps.

```
eox = wmsfind("eox");
```

The wmsfind function returns layers as WMSLayer objects. In this case, the function returned multiple layers. Note that your results might be different because the WMS Database changes each release.

Refine Search

Refine your search based on the WMS Database by using the refine function or based on geographic limits by using the refineLimits function. If your original search provides only one layer, then you do not need to refine your search.

For this example, refine your search to find layers in the WMS Database that also contain blue marble imagery from the NASA Earth Observatory.

```
eox marble = refine(eox, "blue marble");
```

In this case, there are multiple layers in the WMS Database from EOX::Maps that contain blue marble imagery. Refine your search again to find layers with valid latitude limits.

```
eox_marble_limits = refineLimits(eox_marble,"Latlim",[-90 90]);
```

The refined search includes one layer.

Synchronize Layer with Server

Get up-to-date information about the layer by synchronizing it with the web server. The wmsupdate function updates the properties of WMSLayer objects, including the Abstract, CoordRefSysCodes, and Details properties.

Update the layer.

```
eox_update = wmsupdate(eox_marble_limits);
```

Read and Display Map

Read the WMS map from the server by using the wms read function. You can customize the map by specifying properties such as the geographic limits, image dimensions, and background color.

For this example, create an axesm-based map with geographic limits that are appropriate for Europe. Get the current map projection structure (mstruct), which contains properties of the current map.


```
figure
worldmap europe
mstruct = gcm;
latlim = mstruct.maplatlimit;
lonlim = mstruct.maplonlimit;
```

Read the layer as an array and a GeographicCellsReference object, which ties the map to a specific location on Earth. Specify the latitude and longitude limits as the current map limits.

```
[A,R] = wmsread(eox_update,"Latlim",latlim,"Lonlim",lonlim);
```

Display the map. Add a title by specifying the layer title.

```
geoshow(A,R)
title(eox_update.LayerTitle)
plabel off
mlabel off
```



See Also

Functions

wmsfind | wmsupdate | wmsread

Objects

WMSLayer | GeographicCellsReference

More About

- "Basic WMS Terminology" on page 9-2
- "Modify Your Map Request" on page 9-16

Add Legend to WMS Map

WMS servers render layers as images. About 45% of WMS servers in the WMS Database provide legends to help you interpret the pixel colors of the images. You can download the legend image for a layer by accessing the <code>Details.Style.LegendURL</code> field of the WMSLayer object.

This example shows how to read and display a WMS map of surface temperatures, download the associated legend image, and combine the WMS map and legend into a single image.

Read and Display Map

Search the WMS Database for layers from the NASA Goddard Space Flight SVS Image Server, then find the layer that contains urban temperature signatures. Synchronize the layer with the server by using the wmsupdate function. To access the legend image, you must synchronize the layer with the server.

```
layers = wmsfind('svs.gsfc.nasa.gov','SearchField','serverurl');
urban_temperature = refine(layers,'urban*temperature');
urban_temperature = wmsupdate(urban_temperature);


Read and display the layer on a map.

[A,R] = wmsread(urban_temperature);
manFigure = figure;
```

```
mapFigure = figure;
usamap(A,R)
geoshow(A,R)
```

Customize the map by adding city markers, state boundaries, meridian and parallel labels, a north arrow, and a title.

```
latlim = R.LatitudeLimits;
lonlim = R.LongitudeLimits;
GT = readgeotable('worldcities.shp');
cities = geoclip(GT.Shape,latlim,lonlim);
GT = GT(cities.NumPoints ~= 0,:);
geoshow(GT,'MarkerEdgeColor','w','Color','w')
for k=1:height(GT)
    lat = GT(k,:).Shape.Latitude;
    lon = GT(k,:).Shape.Longitude;
    n = GT(k,:).Name;
    textm(lat,lon,n,'Color','w','FontWeight','bold')
end
geoshow('usastatehi.shp', 'FaceColor', 'none',...
   'EdgeColor','black')
mlabel('FontWeight','bold')
plabel('FontWeight','bold')
northarrow('Facecolor','w','EdgeColor','w',...
'Latitude',36.249,'Longitude',-71.173)
title('Urban Temperature Signatures')
```



Search for Legend

Determine if a legend image is available by accessing the Details.Style.LegendURL field of the layer.

urban temperature.Details.Style.LegendURL

```
ans = struct with fields:
   OnlineResource: 'http://svs.gsfc.nasa.gov/vis/a000000/a003100/a003152/temp_bar.png'
        Format: 'image/png'
        Height: 90
        Width: 320
```

The fields are not empty, so a legend is available. Download the legend image.


```
url = urban_temperature.Details.Style.LegendURL.OnlineResource;
legendImage = webread(url);
```

Create a figure and axes that are the same size as the image. Then, display the image. Note that the legend is an image of a colorbar, not a Legend object.

```
sz = size(legendImage);
legendFigure = figure;
pos = legendFigure.Position;
legendFigure.Position = [pos(1) pos(2) sz(2) sz(1)];
```

```
ax = gca;
ax.Units = 'pixels';
ax.Position = [0 0 sz(2) sz(1)];
```

imshow(legendImage)



Combine Map and Legend

When you display images using the **geoshow** function, the map projection might cause text to appear warped. Instead, convert the map into an image and combine the map image with the legend image.

Convert the map into an image by using the getframe and frame2im functions.

mapImage = getframe(mapFigure);

42.5° N Buffalo New York 40.0° N Washington D.C. 77.5° W 75.0° W 72.5° W 70.0° W

mapImage = frame2im(mapImage);

To combine the images, the width of the images must be equal. In this example, the width of the legend image is smaller than the width of the map image. Make the widths the same by padding the legend image.

```
p = (size(mapImage,2) - size(legendImage,2))/2;
legendImage = padarray(legendImage,[0 p 0],255,'both');

Combine the images.

combinedImage = [mapImage; legendImage];


Create a figure and axes that are the same size as the combined image. Display the combined image in the figure.

combinedsz = size(combinedImage);

combinedFigure = figure;
pos = combinedFigure.Position;
combinedFigure.Position = ...
    [pos(1) pos(2) combinedsz(2) combinedsz(1)];

ax = gca;
ax.Units = 'pixels';
ax.Position = [0 0 combinedsz(2) combinedsz(1)];

imshow(combinedImage)
```



See Also

Functions

wmsfind | wmsupdate | wmsread

Objects

WMSLayer

Read WMS Maps Using Different Coordinate Reference Systems

To read a WMS map in the EPSG:4326 coordinate reference system, use the wmsread function. EPSG:4326 is based on the 1984 World Geodetic System (WGS84) datum. All servers in the WMS Database, and presumably all WMS servers in general, use the EPSG:4326 coordinate reference system. This system is a requirement of the OGC® WMS specification.

To read a WMS map in a different coordinate reference system, create a request URL using WebMapServer and WMSMapRequest objects and then read the map using the getMap method. For more information about coordinate reference systems, see Spatial Reference.

This example shows how to read a WMS map with data in Web Mercator coordinates, also known as WGS 84/Pseudo-Mercator coordinates. The Web Mercator coordinate system is commonly used by web applications.

Find Web Mercator Coordinates for Region

Import a GeoTIFF image of Boston as an array and a MapCellsReference object. Find the projected coordinate reference system for the image.

```
[A,R] = readgeoraster('boston.tif');
p_geotiff = R.ProjectedCRS;
```

Unproject the *x*- and *y*-world limits and then reproject them to use the Web Mercator coordinate reference system (EPSG:3857).

```
[latlim,lonlim] = projinv(p_geotiff,R.XWorldLimits,R.YWorldLimits);
p_webmercator = projcrs(3857);
[xlimits,ylimits] = projfwd(p webmercator,latlim,lonlim);
```

To obtain imagery in this coordinate reference system, you must use WMSMapRequest and WebMapServer objects because the wmsread function only reads data in the WGS84 coordinate reference system (EPSG:4326).

Read and Display Map for Region

The USGS National Map provides orthoimagery and topography maps for various regions of the United States. The USGS Imagery Only server provides data in both WGS84 coordinates and Web Mercator coordinates.

Search the WMS Database for the USGS Imagery Only server and select the first layer.


```
doqLayer = wmsfind('usgsimageryonly','SearchField','serverurl');
doqLayer = wmsupdate(doqLayer);

Create WebMapServer and WMSMapRequest objects.


server = WebMapServer(doqLayer.ServerURL);
request = WMSMapRequest(doqLayer,server);
```

Modify the map request by setting properties of the WMSMapRequest object. For this example, specify an image height and width for a sample size of 5 meters. Set the map limits to cover the same region as the GeoTIFF file.


```
metersPerSample = 5;
h = round(diff(ylimits)/metersPerSample);
w = round(diff(xlimits)/metersPerSample);
ylimits = [ylimits(1), ylimits(1) + h*metersPerSample];
xlimits = [xlimits(1), xlimits(1) + w*metersPerSample];
request.CoordRefSysCode = 'EPSG:3857';
request.ImageHeight = h;
request.ImageWidth = w:
request.XLim = xlimits;
request.YLim = ylimits;
Read a map of the orthoimagery in Web Mercator coordinates.
A webmercator = getMap(server, request.RequestURL);
R webmercator = request.RasterReference;
Display the orthoimagery on a map.
figure
mapshow(A webmercator, R webmercator)
axis tight
title({'USGS Digital Ortho-Quadrangle - Boston','Web Mercator'})
Read Boston place names from a shapefile. Unproject and reproject the place names so that they are
in Web Mercator coordinates. Display the place names on the map.
S = shaperead('boston placenames.shp');
x_names = [S.X] * unitsratio('sf','meter');
y names = [S.Y] * unitsratio('sf','meter');
names = \{S.NAME\};
[lat placenames,lon placenames] = projinv(p geotiff, ...
                                           x_names,y_names);
[x_webmercator,y_webmercator] = projfwd(p_webmercator, ...
                                         lat_placenames,lon_placenames);
text(x_webmercator,y_webmercator,names, ...
     BackgroundColor',[0.9 0.9 0],'FontSize',6,'Clipping','on')
```



Compare the map you read from the server to the GeoTIFF image.



You can also compare the maps by using geographic axes and a satellite basemap. When you plot on geographic axes, coordinates are referenced to the WGS84 coordinate reference system.



See Also

Functions

wmsfind|wmsupdate|wmsread|getMap

Objects

WMSMapRequest | WebMapServer | WMSLayer

Related Examples

• "Modify Your Map Request" on page 9-16

Modify Your Map Request

```
In this section...

"Set Map Request Geographic Limits and Time" on page 9-16

"Manually Edit Web Map Request URL" on page 9-17
```

Set Map Request Geographic Limits and Time

A WMSMapRequest object contains properties to modify the geographic extent and time of the requested map. This example shows how to modify your map request to map sea surface temperature for the ocean surrounding the southern tip of Africa. For a complete list of properties, see WMSMapRequest.


Get a list of layers from the capabilities document for the NASA Earth Observations (NEO) WMS server. Refine the search to include only layers with "sea surface temperature" in the layer title or layer name. Refine the search again to include only the layer with monthly values from the MODIS sensor on the Aqua satellite.

```
neoinfo = wmsinfo("https://neo.gsfc.nasa.gov/wms/wms");
neo = neoinfo.Layer;
sst = refine(neo, "sea surface temperature");
sst = refine(sst, "month*modis");
```

Create a WebMapServer object from the server URL stored in the ServerURL property of the layer.

```
server = WebMapServer(sst.ServerURL);
```

Create a WebMapRequest object from the layer and web map server object. Set the latitude and longitude limits by using the Latlim and Lonlim properties. Set the time request to March 1, 2009 by using the Time property.



Read abstract information for the layer from the MetadataURL field.

```
readerFcn = @(filename)readstruct(filename, "FileType", "xml");
options = weboptions("ContentReader", readerFcn, "Timeout", 10);
xml = webread(sst.Details.MetadataURL, options);
abstract = xml.idinfo.descript.abstract;
```

Manually Edit Web Map Request URL

You can modify a map request URL manually.

Search the WMS Database for a layer containing terrain elevation data from the WMS server hosted by MathWorks®. Get the map request URL for the layer.

```
layers = wmsfind("mathworks", "SearchField", "serverurl");
layer = refine(layers, "elevation");
mapRequest = WMSMapRequest(layer);

Set the map request URL to a variable.
mapURL = mapRequest.RequestURL;
```


Specify a background color and request data for the southern hemisphere by manually editing the map request URL. To do this, copy and paste the contents of mapURL into a new variable. Then,

change the background color section of the URL to &BGCOLOR= $0\times2DC1D2$ and change the bounding box section of the URL to &BBOX=-90.0, -180.0.

Read and display the modified map.

```
[A,R] = wmsread(modifiedURL);
figure
axesm globe
axis off
geoshow(A,R)
title("Terrain Data for the Southern Hemisphere")
```

Terrain Data for the Southern Hemisphere



See Also

wmsfind | wmsupdate | wmsread

More About

"Basic Workflow for Creating WMS Maps" on page 9-3

Overlay Multiple Layers

```
In this section...

"Create Composite Map of Multiple Layers from One Server" on page 9-19

"Combine Layers from One Server with Data from Other Sources" on page 9-20

"Drape Orthoimagery Over DEM" on page 9-22
```

Create Composite Map of Multiple Layers from One Server

The WMS specification allows the server to merge multiple layers into a single raster map. The Metacarta VMAP0 server contains many data layers, such as coastlines, national boundaries, ocean, and ground. Read and display a composite of multiple layers from the VMAP0 server. The rendered map has a spatial resolution of 0.5 degrees per cell.


Search the WMS Database for the VMAPO layers. Synchronize the layers you found with the server.

```
vmap0 = wmsfind('vmap0.tiles','SearchField','serverurl');
vmap0 = wmsupdate(vmap0);
```

Create an array of multiple layers that include ground and ocean, coastlines, and national boundaries.

```
layers = [refine(vmap0,'coastline_01'); ...
    refine(vmap0,'country_01'); ...
    refine(vmap0,'ground_01'); ...
    refine(vmap0,'inwater'); ...
    refine(vmap0,'ocean')];
```

Retrieve the composite map. Request a cell size of 0.5 degrees by setting the image height and image width parameters. Set Transparent to true so that all pixels not representing features or data values in a layer are set to a transparent value in the resulting image, making it possible to produce a composite map.



The data used in this example is from Metacarta.

Combine Layers from One Server with Data from Other Sources

This example shows how to merge a boundaries raster map with vector data.

Specify a global raster with 0.5-degree cells by using the <code>georefcells</code> function. Specify columns running north-to-south, for consistency with <code>wmsread</code>. The result R is a geographic raster reference object.


```
latlim = [-90 90];
lonlim = [-180 180];
cellExtent = 0.5;
R = georefcells(latlim,lonlim, ...
    cellExtent,cellExtent,'ColumnsStartFrom','north');
```

Read a shapefile that contains global land area polygons and convert it to a raster map.

```
land = shaperead('landareas.shp','UseGeoCoords',true);
lat = [land.Lat];
lon = [land.Lon];
land = vec2mtx(lat,lon,zeros(R.RasterSize),R,'filled');
```

Read a shapefile that contains world river polylines and convert it to a raster map.

```
riverLines = shaperead('worldrivers.shp', 'UseGeoCoords', true);
rivers = vec2mtx([riverLines.Lat],[riverLines.Lon],land,R);
Merge the rivers with the land.
merged = land:
merged(rivers == 1) = 3;
Get coordinate reference system information from the land areas shapefile by using the shapeinfo
function. The world rivers shapefile uses the same coordinate reference system. Set the
GeographicCRS property of the reference object.
info = shapeinfo('landareas.shp');
R.GeographicCRS = info.CoordinateReferenceSystem;
Read the boundaries image from the VMAP0 server.
vmap0 = wmsfind('vmap0.tiles','SearchField','serverurl');
vmap0 = wmsupdate(vmap0);
layer = refine(vmap0, 'country_01');
height = R.RasterSize(1);
width = R.RasterSize(2);
[boundaries, boundariesR] = wmsread(layer, 'ImageFormat', 'image/png', ...
    'ImageHeight', height, 'ImageWidth', width);
Confirm that the boundaries and merged rasters are coincident.
isequal(boundariesR,R)
ans = logical
Merge the rivers and land with the boundaries.
index = boundaries(:,:,1) \sim = 255 \dots
    & boundaries(:,:,2) ~= 255 ...
    & boundaries(:,:,3) ~= 255;
merged(index) = 1;
Display the result.
figure
worldmap(merged,R)
geoshow(merged,R,'DisplayType','texturemap')
colormap([0.45 0.60 0.30; 0 0 0; 0 0.5 1; 0 0 1])
```



The data used in this example is from the US National Geospatial-Intelligence Agency (NGA) and Metacarta.

Drape Orthoimagery Over DEM


Read elevation data and a geographic postings reference for an area around South Boulder Peak in Colorado. Crop the elevation data to a smaller area using the <code>geocrop</code> function.

```
[fullZ,fullR] = readgeoraster('n39_w106_3arc_v2.dt1','OutputType','double');
latlim = [39.25 40.0];
lonlim = [-106 -105.5];
[Z,R] = geocrop(fullZ,fullR,latlim,lonlim);
```

Display the elevation data. To do this, create an axesm-based map for the United States, plot the data as a surface, and apply an appropriate colormap. View the map in 3-D by adjusting the camera position and target. Set the vertical exaggeration by using the daspectm function.

```
figure
usamap(R.LatitudeLimits,R.LongitudeLimits)
geoshow(Z,R,'DisplayType','surface')
demcmap(Z)
title('Elevation');
```

Elevation



Drape an orthoimage over the elevation data. To do this, first get the names of high-resolution orthoimagery layers from the USGS National Map using the wmsinfo function. In this case, the orthoimagery layer is the only layer from the server. Use multiple attempts to connect to the server in case it is busy.

```
end
end
```


Request a map of the orthoimagery layer using the wmsread function. To display the orthoimagery, use the geoshow function and set the CData property to the layer.

```
imageHeight = size(Z,1);
imageWidth = size(Z,2);

orthoImage = wmsread(orthoLayer, 'Latlim', R.LatitudeLimits, ...
    'Lonlim', R.LongitudeLimits, 'ImageHeight', imageHeight, ...
    'ImageWidth', imageWidth);

figure
usamap(R.LatitudeLimits, R.LongitudeLimits)
geoshow(Z,R, 'DisplayType', 'surface', 'CData', orthoImage);
title('Orthoimage Draped Over Elevation');
set(gca, 'CameraPosition', cameraPosition, ...
    'CameraTarget', cameraTarget)
daspectm('m',3)
```

Orthoimage Draped Over Elevation



The DTED file used in this example is from the US Geological Survey.

See Also

wmsfind | wmsupdate | wmsread

More About

• "Basic Workflow for Creating WMS Maps" on page 9-3

Animate Data Layers

```
In this section...

"Create Movie of Terra/MODIS Maps" on page 9-26

"Create Animated GIF of WMS Maps" on page 9-28

"Create Animation of Time-Lapse Radar Observations" on page 9-29
```

Create Movie of Terra/MODIS Maps

You can create maps of the same geographic region at different times and view them as a movie. For a period of seven days, read and display a daily composite of visual images from NASA's Moderate Resolution Imaging Spectroradiometer (MODIS) scenes captured during the month of December 2010.

Search the NASA Earth Observations (NEO) server for the MODIS layer.

```
neoinfo = wmsinfo("https://neo.gsfc.nasa.gov/wms/wms");
neo = neoinfo.Layer;
modis = refine(neo, "true*color*terra*modis");
modis = wmsupdate(modis);

Create a WebMapServer object and a WMSMapRequest object.
server = WebMapServer(modis.ServerURL);
mapRequest = WMSMapRequest(modis,server);
```

The Extent field provides information about how to retrieve individual frames. You can request a single day because the extent is defined by day ('/P1D'). Note that for December 2010, the frames for December 8 and December 31 are not available.

```
modis.Details.Dimension.Extent

ans =
'2006-09-01/2006-09-14/P1D,2006-09-17/2006-10-10/P1D,2006-10-12/2006-11-18/P1D,2006-11-21/2007-09
```

Create an array indicating the first seven days. Set the start time to December 1, 2010 and use a serial date number.


```
days = 1:7;
time = "2010-12-01";
startTime = datenum(time);
```

Open a figure window with axes appropriate for the region specified by the MODIS layer.

```
hFig = figure;
worldmap(mapRequest.Latlim,mapRequest.Lonlim);
Save each frame to a video file.
videoFilename = "modis_dec.avi";
writer = VideoWriter(videoFilename);
writer.FrameRate = 1;
writer.Quality = 100;
writer.open;
```

Set the Visible property of the figure to 'off' to hide the figure while populating the frames. For each day, read a map of the MODIS layer. Set the Time property to the day number. Ignore data not found on the server or errors issued by the server by using a try/catch statement. For correct indexing, set the start time to one day less.

```
hFig.Visible = "off";
startTime = startTime - 1;
for k = days
    try
        mapRequest.Time = startTime + k;
        timeStr = datestr(mapRequest.Time);
        dailyImage = getMap(server,mapRequest.RequestURL);
        geoshow(dailyImage,mapRequest.RasterReference);
        title({mapRequest.Layer.LayerTitle,timeStr}, ...
             "Interpreter","none","FontWeight","bold")
        frame = getframe(hFig);
        writer.writeVideo(frame);
    catch e
        fprintf(['Server error: %s.\n', ...
             'Ignoring frame number %d on day %s.\n'], ...
            e.message,k,timeStr)
    end
end
writer.close
Read in all video frames.
v = VideoReader(videoFilename);
vidFrames = read(v);
numFrames = get(v,"NumFrames");
Create a movie structure from the video frames.
frames = struct("cdata",[],"colormap",[]);
frames(numFrames) = frames(1);
for k = 1 : numFrames
    frames(k).cdata = vidFrames(:,:,:,k);
    frames(k).colormap = [];
end
Set the Visible property of the figure to 'on' and play the movie once at the frame rate of the
video.
hFig.Visible = "on";
```



movie(hFig, frames, 1, v.FrameRate)

Create Animated GIF of WMS Maps

Read and display an animation of the Larsen Ice Shelf experiencing a dramatic collapse between January 31, 2002 and March 7, 2002.

Search the WMS Database for the phrase 'Larsen Ice Shelf'.

```
iceLayer = wmsfind('Larsen Ice Shelf');
```

Create a WebMapServer by specifying the server URL of the first layer. Synchronize the layer with the server by using the updateLayers function.

```
server = WebMapServer(iceLayer(1).ServerURL);
iceLayer = updateLayers(server,iceLayer(1));
```

Create a WMSMapRequest object.

```
request = WMSMapRequest(iceLayer(1), server);
```

The Extent field provides the available values for a dimension, in this case time. Set the value of the extent to a variable. Calculate the number of required frames.

```
extent = string(iceLayer.Details.Dimension.Extent);
extent = split(extent,",");
numFrames = numel(extent);
```

Create a figure and set up a map with appropriate geographic limits. Customize the appearance of the parallels and meridians.

```
f = figure;
worldmap(request.Latlim,request.Lonlim)
setm(gca,'MLineLocation',1,'MLabelLocation',1, ...
'MLabelParallel',-67.5,'LabelRotation','off');
```

Initialize the value of animated to 0.

```
animated(1,1,1,numFrames) = 0;
```

Set the Visible property of the figure to 'off' to hide the map while populating the frames. Read the image of the Larsen Ice Shelf on different days.

```
f.Visible = 'off';
for k=1:numFrames
    request.Time = extent(k);
    iceImage = getMap(server,request.RequestURL);
    geoshow(iceImage,request.RasterReference)
    title(request.Time,'Interpreter','none')
    frame = getframe(f);
    if k == 1
        [animated, cmap] = rgb2ind(frame.cdata,256,'nodither');
    else
        animated(:,:,1,k) = rgb2ind(frame.cdata,cmap,'nodither');
    end
    pause(2)
end
```

Save the frames as an animated GIF and view the GIF in a browser.

```
filename = 'wmsanimated.gif';
imwrite(animated,cmap,filename,'DelayTime',1.5, ...
   'LoopCount',inf);
web(filename)
```

Create Animation of Time-Lapse Radar Observations

Display Next-Generation Radar (NEXRAD) images for the United States using data from the Iowa Environmental Mesonet (IEM) web map server. The server stores layers covering the past 50 minutes up to the present time in increments of 5 minutes. Read and display the merged layers.

Find layers in the WMS Database that include 'mesonet' and 'nexrad' in their ServerURL fields.

```
mesonet = wmsfind('mesonet*nexrad','SearchField','serverurl');
```

NEXRAD Base Reflect Current ('nexrad-n0r') measures the intensity of precipitation. Refine your search to include only layers with this phrase in one of the search fields.

```
nexrad = refine(mesonet, 'nexrad-n0r', 'SearchField', 'any');
```

Remove the 900913 layers because they are intended for Google MapsTM overlay. Remove the WMST layer because it contains data for different times.

```
layers_900913 = refine(nexrad,'900913','SearchField', ...
    'layername');
layer_wmst = refine(nexrad,'wmst', 'SearchField', 'layername');
rmLayerNames = {layers_900913.LayerName layer_wmst.LayerName};
index = ismember({nexrad.LayerName}, rmLayerNames);
nexrad = nexrad(~index);
```

Update the nexrad layer to fill in all fields and obtain the most recent data.


```
nexrad = wmsupdate(nexrad, 'AllowMultipleServers', true);
```

Create a map of the conterminous United States. Get the latitude and longitude limits of the map.

```
figure
usamap('conus')
mstruct = gcm;
latlim = mstruct.maplatlimit;
lonlim = mstruct.maplonlimit;

Read and display the merged layers.

[A,R] = wmsread(nexrad, 'Latlim', latlim, 'Lonlim', lonlim);
geoshow(A,R)
geoshow('usastatehi.shp', 'FaceColor', 'none')
title({'NEXRAD Radar Map', 'Merged Layers'})
```



Loop through the sequence of time-lapse radar observations. Set the Visible property of the figure to 'off' to hide the figure while populating the frames.

```
hfig = figure('Visible','off');
usamap('conus')
hstates = geoshow('usastatehi.shp', 'FaceColor', 'none');
numFrames = numel(nexrad);
frames = struct('cdata',[],'colormap',[]);
frames(numFrames) = frames;
hmap = [];
frameIndex = 0;
for k = numFrames:-1:1
   frameIndex = frameIndex + 1;
   delete(hmap)
   [A, R] = wmsread(nexrad(k), 'Latlim', latlim, 'Lonlim', lonlim);
   hmap = geoshow(A,R);
   uistack(hstates,'top')
   title(nexrad(k).LaverName)
   frames(frameIndex) = getframe(hfig);
end
Create an array to write out as an animated GIF.
animated(1,1,1,numFrames) = 0;
for k=1:numFrames
   if k == 1
      [animated,cmap] = rgb2ind(frames(k).cdata,256,'nodither');
   else
      animated(:,:,1,k) = \dots
         rgb2ind(frames(k).cdata,cmap,'nodither');
   end
end
Save the animated GIF and view it in a browser.
filename = 'wmsnexrad.gif';
imwrite(animated,cmap,filename,'DelayTime',1.5, ...
   'LoopCount',inf);
web(filename)
```

See Also

wmsfind | wmsupdate | wmsread

More About

"Basic Workflow for Creating WMS Maps" on page 9-3

Display Animation of Radar Images over GOES Backdrop

This example shows how to display NEXRAD radar images. The images cover the past 24 hours, sampled at one-hour intervals, for the United States using data from the IEM WMS server.

Search the WMS Database for the 'nexrad-n0r-wmst' layer. Synchronize the layer with the server.

```
wmst = wmsfind('nexrad-n0r-wmst','SearchField','layername');
wmst = wmsupdate(wmst);
```

Search the WMS Database for a generated CONUS composite of GOES IR imagery. Synchronize the layer with the server.

```
goes = wmsfind('goes*conus*ir','SearchField','layername');
goes = wmsupdate(goes);
```

Create a map of the conterminous United States.

```
hfig = figure;
region = 'conus';
usamap(region)
borders = geoshow('usastatehi.shp','FaceColor','none');
```

Get the latitude and longitude limits of the map.

```
mstruct = gcm;
latlim = mstruct.maplatlimit;
lonlim = mstruct.maplonlimit;
```

Read the GOES layer to use as a backdrop image.

```
cellsize = 0.1;
[backdrop, R] = wmsread(goes, 'ImageFormat', 'image/png', ...
    'Latlim', latlim, 'Lonlim', lonlim, 'Cellsize', cellsize);
```

Find the current time minus 24 hours. Set up frames to hold the data from getframe.

```
now_m24 = datestr(now-1);
hour_m24 = [now_m24(1:end-5) '00:00'];
hour = datenum(hour_m24);
hmap = [];
numFrames = 24;
frames = struct('cdata',[],'colormap',[]);
frames(numFrames) = frames;
```


Set the Visible property of the figure to 'off' to hide the figure while populating the frames. For each hour, obtain the hourly NEXRAD map data and combine it with a copy of the backdrop. Because of how this Web server handles PNG format, the resulting map data has an image with class double. Thus, you must convert it to uint8 before merging.

```
hfig.Visible = 'off';
for k=1:numFrames
    time = datestr(hour);
    [A,R] = wmsread(wmst, 'Latlim', latlim, 'Lonlim', lonlim, ...
    'Time', time, 'CellSize', cellsize, ...
    'BackgroundColor', [0 0 0], 'ImageFormat', 'image/png');
```

```
delete(hmap)
index = any(A > 0, 3);
combination = backdrop;
index = cat(3,index,index,index);
combination(index) = uint8(255*A(index));
hmap = geoshow(combination,R);
uistack(borders, 'top')
title({wmst.LayerName,time})
frames(k) = getframe(hfig);
hour = hour + 1/24;
end
```

Set the Visible property of the figure to 'on'. View the movie loop three times at 1.5 frames per second.

```
hfig.Visible = 'on';
shg
movie(hfig,frames,3,1.5)
```



See Also

wmsfind | wmsupdate | wmsread

More About

"Basic Workflow for Creating WMS Maps" on page 9-3

Read Quantitative Data from WMS Server

WMS servers typically provide layers as images instead of as quantitative data. In some rare cases, you can get quantitative data from specific WMS servers by requesting data in the GeoTIFF or BIL format.

You can determine the formats that a server supports by querying the ImageFormats field of the structure contained within the Details property of a WMS layer.

```
layers = wmsfind("mathworks", "SearchField", "serverurl");
elevation = refine(layers, "elevation");
elevation = wmsupdate(elevation);
elevation.Details.ImageFormats
```

These examples show how to read terrain elevation data from the WMS server hosted by MathWorks and then display the data as a surface or a texture-mapped surface.

Read and Display Terrain Elevation Data

Search the WMS Database for a layer containing terrain elevation data from the WMS server hosted by MathWorks.

```
layers = wmsfind("mathworks", "SearchField", "serverurl");
elevation = refine(layers, "elevation");
```

Read the terrain elevation data from the server for a region surrounding the Gulf of Maine. Specify the sampling interval as 30 arc-seconds and the image format as BIL.

Note that Z is an array containing terrain elevation data rather than an RGB image. Find the minimum and maximum elevation.

```
elevationLimits = [min(min(Z)) max(max(Z))]
elevationLimits = 1 \times 2 int16 row vector
-15 1430
```

Prepare the data for plotting by converting the data type to double. To make the water areas appear blue on the plot, set elevations at sea level (Z == 0) to a value below sea level.

```
Z = double(Z);

Z(Z == 0) = -1;
```

Display the terrain elevation data on a map and plot contour lines at sea level.


```
figure
worldmap(Z,R)
```

```
geoshow(Z,R,"DisplayType","texturemap")
contourm(Z,R,[0 0],"Color","k")
```

Customize the map by adding a title and subtitle, a colormap appropriate for elevation data, and a labeled color bar.

```
title("Gulf of Maine")
st = textwrap(string(elevation.LayerTitle),40);
subtitle(st)
demcmap(Z)

c = colorbar;
c.Label.String = "Elevation (meters)";
```



Merge Elevation Data with Rasterized Vector Data

Read terrain elevation data and rasterized national boundaries for a region. Then, embed the boundaries into the elevation data and display the result on a map.

Read Terrain Elevation Data

Search the WMS Database for a layer containing terrain elevation data from the WMS server hosted by MathWorks.

```
layers = wmsfind("mathworks", "SearchField", "serverurl");
elevation = refine(layers, "elevation");
```

Read the terrain elevation data from the server for a region surrounding Afghanistan. Specify the sampling interval as 1 minute and the image format as BIL.

```
latlim = [25 40];
lonlim = [55 80];
samplingInterval = dms2degrees([0 1 0]);
[ZA,R] = wmsread(elevation, "Latlim", latlim, "Lonlim", lonlim, ...
    "CellSize", samplingInterval, "ImageFormat", "image/bil");
```

Note that ZA is an array of elevation data rather than an RGB image. Find the minimum and maximum elevations.

```
elevationLimits = [min(min(ZA)) max(max(ZA))]
elevationLimits = 1 \times 2 int16 row vector
-13 7350
```


Display Terrain Elevation Data

Prepare the data for plotting by converting the data type to double. To make the water areas appear blue on the plot, set elevations at sea level (ZA == 0) to a value below sea level.

```
ZA = double(ZA);
ZA(ZA == 0) = -1;
Display the elevation data as a texture map.
figure
worldmap("Afghanistan")
geoshow(ZA,R,"DisplayType","texturemap")
demcmap(ZA)
```

subtitle(elevation.LayerTitle)

title("Afghanistan and Surrounding Region")



Read Rasterized Vector Data

Read national boundaries from the Vector Map Level 0 (VMAP0) WMS server as an RGB image. Dark values in the image represent the boundaries.

```
vmap0 = wmsfind("vmap0.tiles", "SearchField", "serverurl");
boundaries = refine(vmap0, "country_02");
B = wmsread(boundaries, "Latlim", latlim, "Lonlim", lonlim, "CellSize", samplingInterval);
```

Merge Elevation and Rasterized Vector Data

To embed the boundaries into the elevation data, find the elements of the boundaries image that contain dark values. Then, replace the corresponding elements of the elevation array with a value slightly higher than the maximum elevation.

```
ZB = ZA;

idx = B(:,:,1) < 250;

ZB(idx) = max(ZA(:)) + 1;
```


Display Merged Data

Display the updated data on a new map.

```
figure
worldmap("Afghanistan")
geoshow(ZB,R,"DisplayType","texturemap")
title("Afghanistan and Country Boundaries")
subtitle(elevation.LayerTitle)
```

Apply a colormap appropriate for elevation data. Use black for the boundaries.

```
cmap = demcmap(ZB);
cmap(end,:,:) = [0 0 0];
colormap(cmap)
```



Drape Basemap Imagery onto Elevation Data

Read basemap imagery and terrain elevation data for a region. Then, create a 3-D map display by draping the basemap imagery over the elevation data.

Read Basemap Imagery

Specify the latitude and longitude limits for a region around the Grand Canyon. Read an image for the region from the "satellite" basemap as an array and as a map cells reference object in Web Mercator coordinates.

```
latlim = [36 36.23];
lonlim = [-113.36 -113.13];
[A,R,attrib] = readBasemapImage("satellite",latlim,lonlim);
```

Read Terrain Elevation Data

WMS servers typically provide data referenced to the World Geodetic System of 1984 (WGS84). If a layer provides data referenced to a different coordinate system, then you can specify the coordinate system by using a web map server object, a WMS map request object, and the <code>getMap</code> function.

Create a web map server object that communicates with the WMS server provided by MathWorks. Get the terrain elevation layer from the capabilities document.

```
serverURL = "https://wms.mathworks.com";
server = WebMapServer(serverURL);
info = getCapabilities(server);
elevation = refine(info.Layer, "elevation");
```

Verify the server provides data referenced to Web Mercator coordinates. The Web Mercator coordinate system has the EPSG code 3857.

elevation.CoordRefSysCodes

```
ans = 2×1 cell
{'EPSG:3857'}
{'EPSG:4326'}
```

Create a map request object for the layer.

- Specify the coordinate system as Web Mercator.
- Specify the image dimensions and world xy-limits so that they match the basemap image.
- Request quantitative elevation data by specifying the image format as BIL.

```
mapRequest = WMSMapRequest(elevation);
mapRequest.CoordRefSysCode = "EPSG:3857";
mapRequest.ImageHeight = size(A,1);
mapRequest.ImageWidth = size(A,2);
mapRequest.XLim = R.XWorldLimits;
mapRequest.YLim = R.YWorldLimits;
mapRequest.ImageFormat = "image/bil";
```

Read the elevation data by using the getMap function.

```
Z = getMap(server,mapRequest.RequestURL);
Z = double(Z);
```

Display Imagery and Elevation Data

Drape the image over the elevation data.

```
figure
mapshow(Z,R,"DisplayType","surface","CData",A)
bmapAttrib = "Basemap from " + attrib;
wmsAttrib = string(elevation.LayerTitle);
title("Grand Canyon")
subtitle(bmapAttrib + ", " + wmsAttrib,"FontSize",8)
axis off
```

Grand Canyon

Basemap from Earthstar Geographics, Terrain elevation data derived from GMTED2010




Adjust the camera view.

campos([-12400000 4240000 152000])
camva(5.4)

Grand Canyon

Basemap from Earthstar Geographics, Terrain elevation data derived from GMTED2010



Tips

- To request quantitative data, you must generally create either a Web Coverage Service (WCS) request or a Web Feature Service (WFS) request. Mapping Toolbox does not support WCS or WFS requests.
- Although BIL files can contain multiple co-registered bands (channels), the BIL files returned by WMS servers include only a single band.
- The wms read function interpolates the elevation data from the WMS server hosted by MathWorks based on the specified latitude and longitude limits. As a result, the data associated with a geographic location varies slightly depending on the limits used to read the data.
- The elevation data from the WMS server hosted by MathWorks does not contain bathymetry data.
- The elevation data from the WMS server hosted by MathWorks does not contain data for a small region within Lake Superior.
- Map request URLs from the WMS server hosted by MathWorks are not supported by web browsers or by the webread function.

See Also

Functions

wmsfind | wmsread | getMap

Objects

WebMapServer|WMSMapRequest

Related Examples

• "Basic Workflow for Creating WMS Maps" on page 9-3

Explore Layers on Same Server

You might find a layer you like in the WMS Database and want to find other layers on the same server. You can explore other layers by using a capabilities document.

Specify the URL of the NASA SVS Image Server. Use the wmsinfo function to return the contents of the capabilities document as a WMSCapabilities object. A *capabilities document* is an XML document containing metadata that describes the geographic content a server offers.

```
serverURL = 'http://svs.gsfc.nasa.gov/cgi-bin/wms?';
capabilities = wmsinfo(serverURL)
capabilities =
  WMSCapabilities
  Properties:
         ServerTitle: 'NASA SVS Image Server'
           ServerURL: 'http://svs.gsfc.nasa.gov/cgi-bin/wms?'
          ServiceName: 'WMS'
             Version: '1.3.0'
      Abstract: 'Web Map Server maintained by the Scientific Visualization Studio at NASA': OnlineResource: 'http://svs.gsfc.nasa.gov/'
  ContactInformation: [1x1 struct]
   AccessConstraints: 'none'
                 Fees: 'none'
         KeywordList: {}
        ImageFormats: {'image/png'}
          LayerNames: {326x1 cell}
                Layer: [326x1 WMSLayer]
          AccessDate: '08-Apr-2021'
  Methods
```


Set the layer titles to a variable. View the first ten titles.

Read the layer containing tropospheric ozone impacts. Display the map.

```
layerTitle = 'Tropospheric Ozone Impacts Global Climate Warming';
layer = refine(capabilities.Layer, layerTitle);
```

```
[A,R] = wmsread(layer);
figure
worldmap(A,R)
geoshow(A,R)
title(layer.LayerTitle)
```

Tropospheric Ozone Impacts Global Climate Warming (644x289 Animation)



This layer contains data from different years. You can examine the available data by accessing the layer.Details.Dimension structure.


layer.Details.Dimension

Display the map for the year 1884 and compare it with the map for 1994, the default year (displayed previously).

```
year = '1884';
[A2,R] = wmsread(layer,'Time',year);
```

figure
worldmap(A2,R)
geoshow(A2,R)
title({layer.LayerTitle,year})

Tropospheric Ozone Impacts Global Climate Warming (644x289 Animation) 1884



See Also

wmsfind | wmsupdate | wmsread

More About


"Basic Workflow for Creating WMS Maps" on page 9-3

Write WMS Layers to KML File

Some WMS server implementations, such as GeoServer, can render their maps in a non-image format, such as KML. KML is an XML dialect used by Google Earth $^{\text{m}}$ and Google Maps $^{\text{m}}$ browsers. The WebMapServer.getMap method and the wms read function do not allow you to use the KML format because they import only standard graphics image formats. Work around this limitation by using the WMSMapRequest.RequestURL property.

Search the WMS Database for layers on any GeoServer. Refine the search to include only the layers from the MassGIS server. Refine the search again to return a FEMA Flood Zone layer.

```
geoserver = wmsfind('geoserver', 'SearchField', 'any');
massgis = refine(geoserver, 'massgis*wms', 'SearchField',...
    serverurl');
floodzone = refine(massgis, 'FEMA Flood Zones', 'SearchField',...
   'LayerTitle');
floodzone = floodzone(1);
Specify geographic limits for a region around Boston, Massachusetts.
latlim = [ 42.305 42.417];
lonlim = [-71.131 - 70.99];
Create a WMSMapRequest object and set the geographic limits.
request = WMSMapRequest(floodzone);
request.Latlim = latlim;
request.Lonlim = lonlim;
Read the graphics image from the server.
[A,R] = wmsread(request.RequestURL);
Display the image on a map.
figure
usamap(A,R)
geoshow(A,R)
```



Request an image format that opens in Google Earth.

```
request.ImageFormat = 'application/vnd.google-earth.kml+xml';
```

Use the websave function to write out a KML file.

```
filename = 'floodzone.kml';
websave(filename,request.RequestURL);
```

Open the file with Google Earth to view. On Windows® platforms, you can display the KML file by uncommenting this code.

```
% winopen(filename)
```

For UNIX® and Mac users, you can display the KML file by uncommenting this code.

```
% cmd = 'googleearth ';
% fullfilename = fullfile(pwd, filename);
% system([cmd fullfilename])
```

See Also

wmsfind | wmsupdate | wmsread | websave

More About

• "Basic Workflow for Creating WMS Maps" on page 9-3

Search for Layers Outside the WMS Database

Search for layers using a web browser instead of using the WMS Database.

Select a search engine. If you are using Google®, select **Images** and enter **getmap** wms into the search box.

Choose a map by viewing the images. Click the map link and find the WMS GetCapabilities request somewhere on the page. If you cannot find a GetCapabilities request, try another map.


For example, this code shows the URL of a WMS GetCapabilities request from the USGS National Map.

Return the capabilities document by using the wmsinfo function.

```
c = wmsinfo(url);
```

Read a layer and display it on a world map.

```
layer = c.Layer(1);
[A,R] = wmsread(layer);
figure
worldmap("world")
geoshow(A,R)
mlabel off
plabel off
title("USGS Imagery")
```



See Also

wmsfind|wmsupdate|wmsread

More About

• "Basic Workflow for Creating WMS Maps" on page 9-3

Create WMS Maps When Internet Access Is Intermittent

Reading data from WMS servers requires Internet access. However, once you read data from a server, you can save the data as a MAT or GeoTIFF file. Then, you can load the data without reading it again from the server. Saving WMS data to files is useful when you have intermittent Internet access, or when you want to share data with someone without Internet access.

This example shows how to create a WMS map for an area around Boston. The behavior of the example depends on whether you have Internet access, but the resulting map is the same.

Throughout the example, specify whether you have Internet access by using the logical scalar useInternet.

- If useInternet is true, read data from the WMS server and update the saved files.
- If useInternet is false, read data from the saved files.

```
useInternet = false;
```

If you use this example as a model to create your own WMS maps, you must create the saved files the first time you run the example by setting useInternet to true.

Search the WMS Database for basemap layers from the USGS National Map [1] on page 9-52. Refine the search to find a layer containing only orthoimagery. This step does not require Internet access, because the WMS Database is installed with Mapping ToolboxTM.

```
bmapLayers = wmsfind("basemap.nationalmap", "SearchFields", "ServerURL");
usgsImageryLayer = refine(bmapLayers, "USGSImageryOnly", "SearchFields", "ServerURL");
```

Synchronize the layer with the server. The wmsupdate function adds an abstract, the attribute and style information, and the coordinate reference system information to the layer.

- If useInternet is true, synchronize the layer with the server. Save the layer to a MAT file.
- If useInternet is false, load the MAT file.

```
if useInternet
    usgsImageryLayer = wmsupdate(usgsImageryLayer);
    save("usgsImageryLayer.mat","usgsImageryLayer")
else
    load usgsImageryLayer.mat
end
```

Specify the geographic limits and the image size. For this example, specify the limits for a region around Boston and a square image with a side length of 750 pixels.

```
latlim = [42.3453 42.3711];
lonlim = [-71.099 -71.0454];
s = 750;
```

Read the image from the server.

- If useInternet is true, then read the map as an array and a GeographicCellsReference object. Save the array and reference object to a GeoTIFF file.
- If useInternet is false, then read the GeoTIFF file.

```
if useInternet
    [A,R] = wmsread(usgsImageryLayer, "Latlim", latlim, "Lonlim", lonlim, ...
    "ImageHeight", s, "ImageWidth", s);
    geotiffwrite("usgsImageryLayer.tif", A,R)
else
    [A,R] = readgeoraster("usgsImageryLayer.tif");
end
```

Create a map with appropriate latitude and longitude limits for the data. Display the map.

figure
usamap(A,R)
geoshow(A,R)



[1] Data available from U.S. Geological Survey, National Geospatial Program.

See Also

Functions

wmsread | wmsupdate

Objects

GeographicCellsReference|WMSLayer

Related Examples

- "Basic Workflow for Creating WMS Maps" on page 9-3
- "Proxy Server Authentication"
- "Use Basemaps in Offline Environments" on page 6-32
- "Display Data over Basemaps When Internet Access Is Intermittent" on page 6-42

Troubleshoot WMS Servers

```
In this section...

"Connection Errors" on page 9-54

"Intermittent Internet Access" on page 9-55

"Geographic Limits in Descending Order or Out of Bounds" on page 9-55

"Non-EPSG:4326 Coordinate Reference Systems" on page 9-55

"Map Not Returned" on page 9-56

"Unsupported WMS Version" on page 9-57

"Other Unrecoverable Server Errors" on page 9-57
```

Connection Errors

One of the challenges of working with WMS is that sometimes you can have trouble connecting to a server.

Time-Out Error

A server might issue a time-out error such as Connection timed out: connect or Read timed out.

Workaround: Try setting the 'TimeoutInSeconds' parameter of the wmsread, wmsinfo, or wmsupdate function to a larger value. The time-out setting defaults to 60 seconds.

Unavailable Server

A server might be temporarily unavailable or busy, or the WMS server application might experience an issue. In some cases, the server issues an HTTP response code of 500, such as:

```
Server returned HTTP response code: 500 for URL: http://xyz.com ...
```

if attempt > numberOfAttempts

Workarounds:

- · Try again later.
- Try requesting a different image format by setting the 'ImageFormat' parameter.
- Try connecting multiple times by using a while loop and try, catch block. For example, this code makes five attempts to get information about the USGS National Map Seamless server. If the connection fails after five attempts, then the code errors.

```
numberOfAttempts = 5;
attempt = 0;
info = [];
serverURL = 'http://basemap.nationalmap.gov/ArcGIS/services/USGSImageryOnly/MapServer/WMSServer
while(isempty(info))
    try
        info = wmsinfo(serverURL);
        orthoLayer = info.Layer(1);
    catch e
    attempt = attempt + 1;
```

```
throw(e);
else
     fprintf('Attempting to connect to server:\n"%s"\n', serverURL)
end
end
end
```

Intermittent Internet Access

You have intermittent Internet access or you want to share WMS data with someone without Internet access.

Workaround: Reading data from WMS servers requires Internet access. However, once you read data from a server, you can save the data as a MAT or GeoTIFF file. Once you save the data, you can load it without reading it again from the server. For more information, see "Create WMS Maps When Internet Access Is Intermittent" on page 9-51.

Geographic Limits in Descending Order or Out of Bounds

Some servers do not follow the OGC specification guidelines regarding latitude and longitude limits.

The OGC specification requires, and the WMS functions expect, that the limits are ascending. However, some sites have descending limits. As a result, you might see an error such as:

```
"??? Error using ==> WMSMapRequest>validateLimit at 1313
Expected the elements of 'Latlim' to be in ascending order."
```

Additionally, some servers have limits that exceed the bounds of [-180,180] for longitude and [-90,90] for latitude.

Workaround: Set the Latlim and Lonlim properties of the WMSLayer object:

```
layers = wmsfind('bluemarbleng');
layer = wmsupdate(layers(1));
latlim = [min(layer.Latlim), max(layer.Latlim)];
lonlim = [min(layer.Lonlim), max(layer.Lonlim)];
layer.Latlim = [max([ -90, latlim(1)]), min([ 90, latlim(2)])];
layer.Lonlim = [max([-180, lonlim(1)]), min([180, lonlim(2)])];
[A,R] = wmsread(layer);
```

You must update your layer before setting the limits. Otherwise, the wmsread function updates the limits from the server, and you once again have unsupported limits.

Non-EPSG:4326 Coordinate Reference Systems

Some layers are not defined in the EPSG:4326 or CRS:84 coordinate reference system. Reading these layers with the wmsread function is not supported.

Workaround: Construct a request URL by using the WMSMapRequest object and read the layer by using the getMap object function. For more information, see "Read WMS Maps Using Different Coordinate Reference Systems" on page 9-11.

Map Not Returned

Sometimes you can connect to the WMS server, but you do not receive the map you are expecting.

Blank Map Returned

A server might return a blank map.

Workaround: You can change the scale of your map; either increase the image height and width or change the geographic bounds. Another possibility is that your requested geographic extent lies outside the extent of the layer, in which case you should change the extent of your request. A third possibility is that you have the wrong image format selected; in this case, change the 'ImageFormat' parameter.

HTML File Returned

% Example command.

You might see this error message:

```
The server returned an HTML file instead of an image file.
```

Workaround: Follow the directions in the error message. The following example, which uses a sample URL, illustrates the type of error message you receive.

```
[A,R] = wmsread(['https://www.mathworks.com?',...
'&BBOX=-180,-90,180,90&CRS=EPSG:4326&VERSION=1.1.1']);

Sample error message:

Error using WebMapServer>issueReadGetMapError (line 974)
The server returned an HTML file instead of an image file.
You may view the complete error message by issuing the command,
   web('https://www.mathworks.com?&BBOX=-180,-90,180,90&CRS=EPSG:4326&VERSION=1.1.1')
   or
   urlread('https://www.mathworks.com?&BBOX=-180,-90,180,90&CRS=EPSG:4326&VERSION=1.1.1').

Error in WebMapServer>readImageFormat (line 874)
        issueReadGetMapError(filename, requestURL);

Error in WebMapServer>readGetMapFile (line 852)
        A = readImageFormat(filename, requestURL);

Error in WebMapServer/getMap (line 299)
        A = readGetMapFile(filename, h.RequestURL);
```

XML File Returned

Error in wmsread (line 376)
A = server.getMap(mapReguestURL);

The server issues a very long error message, beginning with this phrase:

```
An error occurred while attempting to get the map from the server. The error returned is <?xml version="1.0" encoding="utf-8"?> ...
```

Workaround: This problem occurs because the server breaks with the requirements of the OGC standard and returns the XML capabilities document rather than the requested map. Choose a different layer or server.

Unsupported WMS Version

In rare cases, the server uses a different and unsupported WMS version. In this case, you receive an error message such as:

```
The WMS version, '1.2.0', listed in layer.Details.Version is not supported by the server. The supported versions are: '1.0.0' '1.1.0' ^{\prime}1.1.1' '1.3.0' .
```

Workaround: Choose a different server.

Other Unrecoverable Server Errors

The server issues an error indicating that no correction or workaround exists. These cases result in the following types of error messages:

```
Server redirected too many times (20)

An error occurred while attempting to parse the XML capabilities document from the server.

Unexpected end of file from server

An error occurred while attempting to get the map from the server. The server returned a map containing no data.
```

See Also

wmsfind | wmsupdate | wmsread

More About

"Basic Workflow for Creating WMS Maps" on page 9-3

Introduction to Web Map Display


Web maps are interactive maps that are accessed through web pages. As a result, they require a live Internet connection. Using Mapping Toolbox software, you can:

- · Display web maps.
- Interactively or programmatically pan and zoom.
- Select the maps to display, called base layers or basemaps. The webmap function provides a set of basemaps from which you can choose, for example 'Open Street Map'. You can also use WMS Layers and define custom basemaps.
- Add vector data, called overlay layers, such as lines and markers.
- Share your results using printing capabilities or the MATLAB publish command.


Note To display a web map using the toolbox, you must have an Internet connection. MathWorks cannot guarantee the stability and accuracy of web maps, as the servers are located on the Internet and are independent from MathWorks. Occasionally, maps may be slow to display, display partially, or fail to display, because web map servers can become unavailable for short periods of time.

The graphics in web maps are not part of MATLAB graphics.

For example, this image shows the default web map display, including the pan tool, zoom tool, scale bar, Layer Manager expander arrow, and current pointer location.



Open the Layer Manager by clicking the expander arrow in the web map toolbar. Use the Layer Manager to select a basemap layer and display overlay layers.



Web Map Coordinate Systems

When displaying named base layers, or a WMSLayer array in a coordinate reference system of EPSG:900913, the projected coordinate system is "Web Mercator". Otherwise, when displaying a WMSLayer array, the projected coordinate system is EPSG:4326. These projections include a geographic quadrangle bounded north and south by parallels (which map to horizontal lines) and east and west by meridians (which map to vertical lines).

See Also

webmap | wmlimits | wmzoom | wmcenter | wmclose | addCustomBasemap

More About

• "Basic Workflow for Displaying Web Maps" on page 9-61

Basic Workflow for Displaying Web Maps

Workflow Summary

The web map display is an interactive capability, so there is no specific workflow required. The following is one way to approach working with web map displays.

- Display the default web map, using the webmap function. You can also specify a base layer (also called a basemap) when you create the web map with the webmap function.
- 2 Select a base layer map from the Layer Manager. The toolbox supports over a dozen base layers from popular web map providers. You can also add custom base layers.
- Navigate around the web map, using the zoom tool and moving the map interactively (panning). You can also specify the visible portion of the web map programmatically using the wmlimits, wmzoom, and wmcenter functions.
- 4 Select additional layers to overlay on your web map from the overlay layers listed in the Layer Manager. You can also create overlay layers using the wmline, wmmarker, and wmpolygon functions. Use wmremove to remove layers that you've added.
- **5** Print the map, using the wmprint function.
- **6** Close the map, using the wmclose function.

See Also


More About

- "Introduction to Web Map Display" on page 9-58
- "Display a Web Map" on page 9-62
- "Select a Base Layer Map" on page 9-63
- "Specify a Custom Base Layer" on page 9-65

Display a Web Map

To display web map data, use the webmap function. By default, webmap displays the World Street Map, centered at latitude and longitude [0 0], but you select other base layers from the Layer Manager. Web maps are interactive, which means you can navigate the map interactively by using the pan and zoom controls, your mouse, or the arrow keys. By default, you can pan across the map continuously, across the 180 meridian.

webmap



See Also


webmap

More About

- "Basic Workflow for Displaying Web Maps" on page 9-61
- "Select a Base Layer Map" on page 9-63

Select a Base Layer Map

Once you open a web map, you can change the base layer (basemap) by using the Layer Manager. To open the Layer Manager, select the expander arrow on the right side of the window. For example, change the basemap to Light Gray Canvas Map. This map is useful for displaying vector data.



Close the Layer Manager.



You can also specify the base layer programmatically when you open the web map, by including the name of the layer as an argument to the webmap function. The following example opens the web map, displaying the Light Gray Canvas Map. For a list of all the named base layers supported, see the webmap function. The examples includes the optional parameter Wraparound that causes the map display to be truncated at the -180 degree and +180 degree meridians. By default, maps are continuous.

webmap('Light Gray Canvas Map','WrapAround',false)

See Also

webmap | wmsfind | wmsupdate

More About

"Basic Workflow for Displaying Web Maps" on page 9-61

Specify a Custom Base Layer

The webmap function provides a selection of over a dozen base layers (basemaps) which provide a variety of geographic backdrops on which you can plot your data. See the webmap function for a complete list. In some cases, you might want to plot your data over a map of your own choosing. To do this, specify a custom base layer by using the addCustomBasemap function. The following example shows how to specify a high-resolution topographical map as a custom base layer.

1 Specify the URL of the website that provides the map data. In this example, for better load balancing, the web map provides three servers that you can use: a, b, or c.

```
url = 'a.tile.opentopomap.org';
```

2 Define the name that you will use to specify the custom base layer programmatically. For example, you can use this name with the webmap command or, if you want to delete the custom map, with the removeCustomBasemap function.

```
name = 'opentopomap';
```

3 Create an attribution to display on the map that gives credit to the provider of the map data. Web map providers might define specific requirements for the attribution.

4 Define the name that will appear in the Layer Manager to identify the custom base layer.

```
displayName = 'Open Topo Map';
```

5 Add the custom base layer to the list of base layers available through the Layer Manager. When you add a custom base layer, the addition is persistent between MATLAB sessions.

Open a web map. Expand the Layer Manager and find the listing for the custom base layer in the list of base layers. To view the custom base layer, select the map in the Layer Manager. You can also specify the name you assigned to the map as an argument to the webmap function.

```
webmap opentopomap
```



See Also

webmap | addCustomBasemap | removeCustomBasemap

More About

- "Basic Workflow for Displaying Web Maps" on page 9-61
- "Specify a WMS Layer as a Base Layer" on page 9-67

Specify a WMS Layer as a Base Layer

Display a WMS layer in a web map by using the webmap function. The following example shows how to use Web Map Service functions to connect with a Web server, retrieve a layer, and display it in a web map. Change the view using your mouse.



Web maps do not support layers from wms.mathworks.com.

See Also


webmap | wmsfind | wmsupdate

More About


- "Basic Workflow for Displaying Web Maps" on page 9-61
- "Specify a Custom Base Layer" on page 9-65

Add an Overlay Layer to the Map

Add a layer of vector data over the base layer map by using the Layer Manager. For example open a web map by calling the webmap function and then open the Layer Manager by clicking the expander arrow \(^4\). Then, choose the **Light Gray Canvas Map** base layer and overlay the **World Boundaries** (**Dark Text**) vector data.



Close the layer manager and then navigate the map using your mouse or arrow keys.



See Also

webmap | wmsfind | wmsupdate

More About

"Basic Workflow for Displaying Web Maps" on page 9-61

Add Line, Polygon, and Marker Overlay Layers to Web Maps

This example shows how to add line, polygon, and marker overlay layers to a web map. Overlay layers can add information, such as, state borders and coast lines, to a base layer map. The toolbox includes functions to draw lines, polygons, and web markers on a web map.

For example, to draw a multifaceted line or multiple lines on a map, use the wmline function. You use latitude and longitude values to specify the points that define the line. Similarly, to draw a polygon, use the wmpolygon function, specifying latitude and longitude values that define the vertices of the polygon. You can also add markers, or map pins, to identify points of interest on a web map using the wmmarker function.


The following example illustrates these capabilities.

1 Load latitude and longitude data. This creates two variables in the workspace: coastlat and coastlon.


load coastlines

2 Use the latitude and longitude data to define a line overlay. wmline draws the overlay on the current web map or, if none exists, it creates a new web map. The example includes several optional parameters to specify the line width and the name you want associated with the line.

```
wmline(coastlat,coastlon,'LineWidth',3,'FeatureName','coastline')
```




3 The wmline command adds the new overlay to the list of overlays in the Layer Manager. By default, this layer is called **Line Overlay 1**.




4 Use the same latitude and longitude data to define a polygon overlay. wmpolygon interprets the latitudes and longitudes as the vertices of a polygon, and draws the overlay on the current web map. The example includes several optional parameters to specify the line width and the name you want associated with the line.

wmpolygon(coastlat,coastlon,'FeatureName','coastline','FaceColor','green')




5 The wmpolygon command adds the polygon overlay to the list of overlays in the Layer Manager. By default, this layer is called **Polygon Overlay 2**.



Add a marker to the web map by using the wmmarker function. Display information about the marker by clicking on it. The wmmarker function adds the marker overlay to the list of overlays in the Layer Manager. By default, this layer is called **Marker Overlay 3**.

```
wmmarker(10.5000,-66.8992,'FeatureName','Caracas')
```



See Also

webmap | wmline | wmpolygon | wmmarker | wmremove

More About

• "Basic Workflow for Displaying Web Maps" on page 9-61

Remove Overlay Layers on a Web Map


To remove an overlay layer on a web map, use the wmremove function. When called without an argument, wmremove deletes the most recently added overlay layer. You can also remove a particular overlay by specifying the handle of the line or marker overlay. The following example illustrates this capability.

1 Load latitude and longitude data. This command loads two variables into the workspace: coastlat and coastlon.

load coastlines


Add a line overlay of the coastline data and set the overlay to a variable using the wmline function. There is no current web map, so wmline creates one.

h = wmline(coastlat,coastlon,'Width',3,'FeatureName','coastline');




Add a marker overlay and set it to a variable using the wmmarker function. The marker highlights the location of the city of Caracas. Note that the overlays are listed in the Layer Manager as Line Overlay 1 and Marker Overlay 2.

h2 = wmmarker(10.5000,-66.8992,'FeatureName','Caracas');




Remove one of the overlays by using the wmremove function. When called without an argument, wmremove deletes the most recent overlay. In this case, wmremove removes the marker overlay. The wmremove function also removes the marker entry in the Layer Manager.

wmremove



5 Remove a particular overlay by specifying it when you call wmremove. For example, remove the line overlay.

wmremove(h)



See Also

webmap | wmline | wmpolygon | wmmarker | wmremove

More About

• "Basic Workflow for Displaying Web Maps" on page 9-61

Navigate a Web Map

Web maps created using the webmap function are interactive. View a portion of the map in more detail by using the zoom control or scroll wheel. Move the map in any direction by using the pan tool or arrow keys, or clicking and dragging the mouse. Alternatively, you can position the map programmatically using the wmzoom, wmlimits, and wmcenter functions.

For example, open a web map using the webmap function. By default, webmap displays the entire map, scaled to fit the window and centered at latitude and longitude [0 0]. This image shows the pan tool outlined in red and the zoom tool outlined in blue. Use the tools to center the map on Brazil.

webmap



You can perform the same navigation programmatically. For example, open a web map that is centered on Brazil using the wmcenter function. Specify the latitude and longitude of the center point and the zoom level as arguments.

wmcenter(-15.6000,-56.1003,4)

You can also customize your view of a web map by specifying the latitude and longitude limits. For example, retrieve the current latitude and longitude limits using the wmlimits function. Depending on the size of the web map, your limits may be different.

```
[latlim,lonlim] = wmlimits
latlim =
    -36.5081     7.6476

lonlim =
    -88.7077     -23.4929
```

You can then open a new web map, specifying these latitude and longitude limits using the wmlimits function.

```
wmlimits(latlim,lonlim)
```

The displayed limits may not match the specified limits because the zoom level is quantized to discrete integer values and the longitude limits may be constrained.

See Also

webmap | wmsfind | wmsupdate | wmcenter

More About

• "Basic Workflow for Displaying Web Maps" on page 9-61

Close a Web Map

To programmatically close a web map, use the wmclose function.

When called without an argument, wmclose closes the current web map. You can also specify which web map to close by specifying a handle to the web map. To close all currently open web maps, call wmclose specifying the 'all' argument.

The following example opens several web maps, closes a specific web map, and then closes all open web maps.

1 Open several web maps, getting the handles to the web maps.

```
wm1 = webmap;
wm2 = webmap('Light Gray');
wm3 = webmap('Open Street');
```

2 Close a specific web map, using its handle.

```
wmclose(wm3)
```

3 Close all web maps that remain open. You can also use the command form: wmclose all.

```
wmclose('all')
```

See Also

webmap|wmclose

More About


• "Basic Workflow for Displaying Web Maps" on page 9-61

Annotate a Web Map with Measurement Information


This example shows how to use a map to get information about a geographic feature. To illustrate, this example measures the length of the Gross Reservoir and adds some markers and a line overlay that act as annotations on the map.

Open a web map centered on the Gross Reservoir west of Boulder, Colorado. Use the USGS Shaded Topographic Map to get the level of topographical detail required for this measurement.

```
webmap('usgsshadedtopographicmap')
lat = 39.9428;
lon = -105.3691;
zoom = 14;
wmcenter(lat,lon,zoom)
```



Identify two points at opposite ends of the lake and get the latitude and longitude of these points. To get this information in a web map, move the mouse pointer over a location on the map. In the upper right corner, the window displays the geographic coordinates of the point.



Store the latitude and longitude information in a geoshape vector.


```
lat1 = 39.93504;
lon1 = -105.38069;
lat2 = 39.95226;
lon2 = -105.35892;
s = geoshape([lat1 lat2],[lon1 lon2])
s =

1×1 geoshape vector with properties:
    Geometry: 'line'
    Metadata: [1×1 struct]
Vertex properties:
    Latitude: [39.9350 39.9523]
    Longitude: [-105.3807 -105.3589]
```

Calculate the distance between the two points to get the length of the reservoir. Use the distance function which calculates the distance between points on a sphere or ellipsoid.

Display a line between the two points. Include information about the length of the lake in the line's information balloon. Store the distance and information about units as two dynamic fields added to the geoshape vector.

```
s.Distance = round(d);
s.Units = 'meters';
wmline(s,'Color','red','FeatureName','Length of Gross Reservoir', ...
'Overlayname','Transect');
```



See Also

webmap | wmsfind | wmsupdate | wmmarker | wmline | wmpolygon | wmremove | geoshape

More About

• "Basic Workflow for Displaying Web Maps" on page 9-61

Compositing and Animating Web Map Service (WMS) Meteorological Layers

This example shows how to composite and animate data from multiple Web Map Service (WMS) layers.

The base layer is from the NASA Goddard Space Flight Center's Scientific Visualization Studio (SVS) Image Server. The data in this layer shows satellite cloud data during Hurricane Katrina from August 23 through August 30, 2005. The layer consists of cloud data extracted from GOES-12 imagery and overlaid on a color image of the southeast United States.

Next-Generation Radar (NEXRAD) images, collected by the Iowa State University's Iowa Environmental Mesonet (IEM) Web map server, are composited with the cloud data at regular intervals of time.

In particular, this example will show you how to:

- · Use the WMS database to find the Katrina and NEXRAD layers
- Retrieve the Katrina base map from a WMS server at a particular time-step
- Retrieve the NEXRAD map from a WMS server at the same time-step
- Composite the base map with the map containing the NEXRAD imagery
- View the composited map in a projected coordinate system
- Retrieve, composite, and animate multiple time sequences
- Create a video file and animated GIF file of the animation

Understanding Basic WMS Terminology

If you are new to WMS, several key concepts are important to understand and are listed here.

- Web Map Service --- The Open Geospatial Consortium (OGC) defines a Web Map Service (WMS) to be an entity that "produces maps of spatially referenced data dynamically from geographic information."
- WMS server --- A server that follows the guidelines of the OGC to render maps and return them to clients
- *map* --- The OGC definition for map is "a portrayal of geographic information as a digital image file suitable for display on a computer screen."
- *layer* --- A dataset of a specific type of geographic information, such as temperature, elevation, weather, orthophotos, boundaries, demographics, topography, transportation, environmental measurements, and various data from satellites
- *capabilities document ---* An XML document containing metadata describing the geographic content offered by a server

Source Function

The code shown in this example can be found in this function:

function mapexwmsanimate(useInternet,datadir)

Internet Access

Since WMS servers are located on the Internet, this example can be set to access the Internet to dynamically render and retrieve maps from WMS servers or it can be set to use data previously retrieved from the Internet using the WMS capabilities but now stored in local files. You can use a variable, useInternet, to determine whether to read data from locally stored files, or retrieve the data from the Internet.

If the useInternet flag is set to true, then an Internet connection must be established to run the example. Note that the WMS servers may be unavailable, and several minutes may elapse before the maps are returned. One of the challenges of working with WMS servers is that sometimes you will encounter server errors. A function, such as wmsread, may time out if a server is unavailable. Often, this is a temporary problem and you will be able to connect to the server if you try again later. For a list of common problems and strategies for working around them, please see the Common Problems with WMS Servers section in the Mapping ToolboxTM User's Guide.

You can store the data locally the first time you run the example and then set the useInternet flag to false. If the useInternet flag is not defined, it is set to false.

```
if ~exist('useInternet', 'var')
    useInternet = false;
end
```

Setup: Define a Data Directory and Filename Utility Function

This example writes data to files if useInternet is true or reads data from files if useInternet is false. It uses the variable datadir to denote the location of the folder containing the data files.

```
if ~exist('datadir','var')
    datadir = fullfile(matlabroot,'examples','map','data');
end
if ~exist(datadir,'dir')
    mkdir(datadir)
end
```

Define an anonymous function to prepend datadir to the input filename:

```
datafile = @(filename) fullfile(datadir,filename);
```

Step 1: Find Katrina Layers From Local Database

One of the more challenging aspects of using WMS is finding a WMS server and then finding the layer that is of interest to you. The process of finding a server that contains the data you need and constructing a specific and often complicated URL with all the relevant details can be very daunting.

The Mapping Toolbox™ simplifies the process of locating WMS servers and layers by providing a local, installed, and pre-qualified WMS database, that is searchable, using the function wmsfind. You can search the database for layers and servers that are of interest to you. Here is how you find layers containing the term katrina in either the LayerName or LayerTitle field of the database:

katrina(1)

The search for the term 'katrina' returned a WMSLayer array containing multiple layers. To inspect information about an individual layer, simply display it like this:

If you type, katrina, in the command window, the entire contents of the array are displayed, with each element's index number included in the output. This display makes it easy for you to examine the entire array quickly, searching for a layer of interest. You can display only the LayerTitle property for each element by executing the command:

```
disp(katrina, 'Properties', 'layertitle', 'Index', 'off', 'Label', 'off');
```

As you've discovered, a search for the generic word 'katrina' returned results of many layers and you need to select only one layer. In general, a search may even return thousands of layers, which may be too large to review individually. Rather than searching the database again, you may refine your search by using the refine method of the WMSLayer class. Using the refine method is more efficient and returns results faster than wmsfind since the search has already been narrowed to a smaller set. Supplying the query string, 'goes-12*katrina*visible*close*up*animation', to the refine method returns a WMSLayer array whose elements contain a match of the query string in either the LayerTitle or LayerName properties. The * character indicates a wild-card search. If multiple entries are returned, select only the first one from the svs.gsfc.nasa.gov server.

```
katrina = refine(katrina,'goes-12*katrina*visible*close*up*animation');
katrina = refine(katrina,'svs.gsfc.nasa.gov','Searchfield','serverurl');
katrina = katrina(1);
whos katrina

Name Size Bytes Class Attributes

katrina 1x1 466 WMSLayer
```

Step 2: Synchronize WMSLayer Object with Server

The database only stores a subset of the layer information. For example, information from the layer's abstract, details about the layer's attributes and style information, and the coordinate reference system of the layer are not returned by wmsfind. To return all the information, you need to use the wmsupdate function. wmsupdate synchronizes the layer from the database with the server, filling in the missing properties of the layer.

Synchronize the first katrina layer with the server in order to obtain the abstract information. Since this action requires access to the Internet, call wmsupdate only if the useInternet flag is true.

```
cachefile = datafile('katrina.mat');
if useInternet
    katrina = wmsupdate(katrina);
    if ~exist(cachefile,'file')
        save(cachefile,'katrina')
    end
else
    cache = load(cachefile);
    katrina = cache.katrina;
end
```

Display the abstract information of the layer. Use isspace to help determine where to line wrap the text.

```
abstract = katrina.Abstract;
endOfLine = find(isstrprop(abstract,'cntrl'),1);
abstract = abstract(1:endOfLine);
numSpaces = 60;
while(~isempty(abstract))
    k = find(isspace(abstract));
    n = find(k > numSpaces,1);
    if ~isempty(n)
        fprintf('%s\n',abstract(1:k(n)))
        abstract(1:k(n)) = [];
else
        fprintf('%s\n',abstract)
        abstract = '';
end
end
```

The GOES-12 satellite sits at 75 degrees west longitude at an altitude of 36,000 kilometers over the equator, in geosynchronous orbit. At this position its Imager instrument takes pictures of cloud patterns in several wavelengths for all of North and South America, a primary measurement used in weather forecasting. The Imager takes a pattern of pictures of parts of the Earth in several wavelengths all day, measurements that are vital in weather forecasting. This animation shows a daily sequence of GOES-12 images in the visible wavelengths, from 0.52 to 0.72 microns, during the period that Hurricane Katrina passed through the Gulf of Mexico. At one kilometer resolution, the visible band measurement is the highest resolution data from the Imager, which accounts for the very high level of detail in these images. For this animation, the cloud data was extracted from GOES image and laid over a background color image of the southeast United States.

Note that this abstract information, including any typographical issues and incomplete fragments, was obtained directly from the server.

Step 3: Explore Katrina Layer Details

You can find out more information about the katrina layer by exploring the Details property of the katrina layer. The Details.Attributes field informs you that the layer has fixed width and fixed height attributes, thus the size of the requested map cannot be modified.

katrina.Details.Attributes

The Details.Dimension field informs you that the layer has a time dimension

katrina.Details.Dimension

with an extent from 2005-08-23T17:45Z to 2005-08-30T17:45Z with a period of P1D (one day), as shown in the Details.Dimension.Extent field.

katrina.Details.Dimension.Extent

```
ans = '2005-08-23T17:45Z/2005-08-30T17:45Z/P1D'
```

Step 4: Retrieve Katrina Map from Server

Now that you have found a layer of interest, you can retrieve the raster map using the function wmsread and display the map using the function geoshow. Since Time is not specified when reading the layer, the default time, 2005-08-30T17:45Z, is retrieved as specified by the Details.Dimension.Default field. If the useInternet flag is set to true, then cache the image and referencing matrix in a GeoTIFF file.


```
cachefile = datafile('katrina.tif');
if useInternet
    [katrinaMap,R] = wmsread(katrina);
    if ~exist(cachefile,'file')
        geotiffwrite(cachefile,katrinaMap,R)
    end
else
```

```
[katrinaMap,R] = readgeoraster(cachefile);
end
```

Display the katrinaMap and overlay the data from the usastatehi.shp file.

```
states = readgeotable('usastatehi.shp');
figure
usamap(katrina.Latlim, katrina.Lonlim)
geoshow(katrinaMap,R)
geoshow(states,'FaceColor','none')
title({katrina.LayerTitle, katrina.Details.Dimension.Default}, ...
'Interpreter','none')
```

GOES-12 Imagery of Hurricane Katrina: Visible Close-up (1024x1024 Animation 2005-08-30T17:45Z



Step 5: Find NEXRAD Radar Layer

NEXRAD radar images for the United States are stored on the Iowa State University's IEM Web map server. The server conveniently stores NEXRAD images in five minute increments from 1995-01-01 to the present time. You can find the layer by first searching for the term IEM WMS Service in the ServerTitle field of the WMS database, then refining the search by requesting the layer of interest, nexrad-n0r-wmst.

```
iemLayers = wmsfind('IEM WMS Service','SearchField','servertitle');
nexrad = refine(iemLayers,'nexrad-n0r-wmst');
Synchronize the layer with the server.
cachefile = datafile('nexrad.mat');
if useInternet
```

```
nexrad = wmsupdate(nexrad);
  if ~exist(cachefile,'file')
      save(cachefile,'nexrad')
  end
else
  cache = load(cachefile);
  nexrad = cache.nexrad;
end
```

Step 6: Obtain Extent Parameters

To composite the nexrad layer with the katrina layer, you need to obtain the nexrad layer at coincidental time periods, and concurrent geographic and image extents. The Details.Dimension field informs you that the layer has a time dimension,

nexrad.Details.Dimension

and the Details.Dimension.Default field informs you that the layer's time extent includes seconds.

nexrad.Details.Dimension.Default

```
ans = '2006-06-23T03:10:00Z'
```

Obtain a time value coincidental with the katrina layer, and add seconds to the time specification.

```
nexradTime = [katrina.Details.Dimension.Default(1:end-1) ':00Z'];
```

Assign latlim and lonlim variables to specify the limits for the nexrad layer. Set the values to the limits of the katrina layer so that the geographic areas match. Note that the nexrad layer's southern latitude limit does not extend as far south as the katrina layer's southern latitude limit. The values that lie outside the geographic bounding quadrangle of the nexrad layer are set to the background color.

```
fprintf('%s%d\n','Southern latitude limit of NEXRAD layer: ',nexrad.Latlim(1))
fprintf('%s%d\n','Southern latitude limit of Katrina layer: ',katrina.Latlim(1))
Southern latitude limit of NEXRAD layer: 24
Southern latitude limit of Katrina layer: 10
```


```
latlim = katrina.Latlim;
lonlim = katrina.Lonlim;
Assign imageHeight and imageWidth variables.
imageHeight = katrina.Details.Attributes.FixedHeight;
imageWidth = katrina.Details.Attributes.FixedWidth;
```

Step 7: Retrieve NEXRAD Radar Map from Server

You can retrieve the nexradMap from the server, specified at the same time as the katrinaMap and for the same geographic and image extents, by supplying parameter/value pairs to the wmsread function. To accurately retrieve the radar signal from the map, set the ImageFormat parameter to the image/png format. In order to easily retrieve the signal from the background, set the background color to black ($[0\ 0\ 0]$).

Retrieve the nexradMap.

```
black = [0 \ 0 \ 0];
cachefile = datafile('nexrad.tif');
if useInternet
     [nexradMap,R] = wmsread(nexrad, ...
          'Latlim', latlim, 'Lonlim', lonlim, 'Time', nexradTime, ... 'BackgroundColor', black, 'ImageFormat', 'image/png', ... 'ImageHeight', imageWidth', imageWidth);
     if ~exist(cachefile, 'file')
          geotiffwrite(cachefile,nexradMap,R)
    end
else
     [nexradMap,R] = readgeoraster(cachefile);
end
Display the nexradMap.
figure
usamap(latlim,lonlim)
geoshow(nexradMap,R)
geoshow(states, 'FaceColor', 'none', 'EdgeColor', [0.9 0.9 0.9])
title({nexrad.LayerTitle, nexradTime}, 'Interpreter', 'none');
```



Step 8: Composite NEXRAD Radar Map with Katrina Map

To composite the nexradMap with a copy of the katrinaMap, you need to identify the non-background pixels in the nexradMap. The nexradMap data is returned as an image with class double, because of how this web map server handles PNG format, so you need convert it to uint8 before merging.

Identify the pixels of the nexradMap image that do not contain the background color.

Composited with NEXRAD Radar 2005-08-30T17:45:00Z

GOES 12 Imagery of Hurricane Katrina

Step 9: Initialize Variables to Animate the Katrina and NEXRAD Maps

The next step is to initialize variables in order to animate the composited katrina and nexrad maps.

Create variables that contain the time extent of the katrina layer.

```
extent = katrina.Details.Dimension.Extent;
slash = '/';
slashIndex = strfind(extent,slash);
startTime = extent(1:slashIndex(1)-1);
endTime = extent(slashIndex(1)+1:slashIndex(2)-1);
```

Calculate numeric values for the start and end days. Note that the time extent is in yyyy-mm-dd format.

```
hyphen = '-';
hyphenIndex = strfind(startTime,hyphen);
dayIndex = [hyphenIndex(2) + 1, hyphenIndex(2) + 2];
startDay = str2double(startTime(dayIndex));
endDay = str2double(endTime(dayIndex));
```

Assign the initial katrinaTime.

```
katrinaTime = startTime;
```

Since multiple requests to a server are required for animation, it is more efficient to use the ${\tt WebMapServer}$ and ${\tt WMSMapRequest}$ classes.

Construct a WebMapServer object for each layer's server.

```
nasaServer = WebMapServer(katrina.ServerURL);
iemServer = WebMapServer(nexrad.ServerURL);
Create WMSMapRequest objects.
katrinaRequest = WMSMapRequest(katrina, nasaServer);
nexradRequest = WMSMapRequest(nexrad, iemServer);
Assign properties.
nexradRequest.Latlim = latlim;
nexradRequest.Lonlim = lonlim;
nexradRequest.BackgroundColor = black;
nexradRequest.ImageFormat = 'image/png';
nexradRequest.ImageHeight = imageHeight;
nexradRequest.ImageWidth = imageWidth;
```

Step 10: Create Animation Files

An animation can be viewed in the browser when the browser opens an animated GIF file or an AVI video file. To create the animation frames of the WMS basemap and vector overlays, create a loop through each day, from startDay to endDay, and obtain the katrinaMap and the nexradMap for that day. Composite the maps into a single image, display the image, retrieve the frame, and store the results into a frame of an AVI file and a frame of an animated GIF file.

To share with others or to post to web video services, create an AVI video file containing all the frames using the VideoWriter class.

```
videoFilename = fullfile(pwd,'wmsanimated.avi');
if exist(videoFilename,'file')
         delete(videoFilename)
end
writer = VideoWriter(videoFilename);
writer.FrameRate = 1;
writer.Quality = 100;
open(writer)
```

The animation is viewed in a single map display. Outside the animation loop, create a map display. Initialize hmap, used in the loop as the return handle from the function geoshow, so it can be deleted on the first pass through the loop. Loop through each day, retrieve and display the WMS map, and save the frame.

```
fig = figure;
usamap(latlim,lonlim)
hstates = geoshow(states,'FaceColor','none');
hmap = [];

for k = startDay:endDay

  % Update the time values and assign the Time property for each server.
    currentDay = num2str(k);
    katrinaTime(dayIndex) = currentDay;
    nexradTime = [katrinaTime(1:end-1) ':00Z'];
    katrinaRequest.Time = katrinaTime;
    nexradRequest.Time = nexradTime;
```


```
% Retrieve the WMS map of Katrina from the server (or file)
% for this time period.
cachefile = datafile(['katrina_' num2str(currentDay) '.tif']);
if useInternet
    katrinaMap = getMap(nasaServer, katrinaRequest.RequestURL);
    if ~exist(cachefile, 'file')
        geotiffwrite(cachefile, katrinaMap, katrinaRequest.RasterRef)
    end
else
    katrinaMap = readgeoraster(cachefile);
end
% Retrieve the WMS map of the NEXRAD imagery from the server (or file)
% for this time period.
cachefile = datafile(['nexrad ' num2str(currentDay) '.tif']);
if useInternet
    nexradMap = getMap(iemServer, nexradRequest.RequestURL);
    if ~exist(cachefile, 'file')
        geotiffwrite(cachefile, nexradMap, nexradRequest.RasterRef)
    end
else
    nexradMap = readgeoraster(cachefile);
end
% Identify the pixels of the nexradMap image that do not contain the
% background color.
index = any(nexradMap > threshold, 3);
index = repmat(index,[1 1 3]);
% Composite nexradMap with katrinaMap.
combination = katrinaMap;
combination(index) = uint8(nexradMap(index)*255);
% Delete the old map and display the new composited map.
delete(hmap)
hmap = geoshow(combination, katrinaRequest.RasterRef);
uistack(hstates, 'top')
title({'GOES 12 Imagery of Hurricane Katrina', ...
    'Composited with NEXRAD Radar',nexradTime})
drawnow
% Save the current frame as an RGB image.
currentFrame = getframe(fig);
RGB = currentFrame.cdata;
% Create an indexed image for each RGB frame in order to display an
% animated GIF.
if k == startDay
    % The first time through the loop, convert the RGB image to
    % an indexed image and save the colormap into the
    % variable, cmap. Use cmap to convert later frames.
    [frame, cmap] = rgb2ind(RGB, 256, 'nodither');
    % Use the size of the first frame and the total
    % number of frames to initialize animated with
    % a size large enough to contain all the frames.
    frameSize = size(frame);
    numFrames = endDay - startDay + 1;
```

```
animated = zeros([frameSize 1 numFrames],'like',frame);
else
    % Use the colormap from the first frame conversion and
    % convert this frame to an indexed image.
    frame = rgb2ind(RGB,cmap,'nodither');
end

% Store the frame into the animated array for the GIF file.
frameCount = k - startDay + 1;
animated(:,:,1,frameCount) = frame;

% Write the RGB frame to the AVI file.
writeVideo(writer,RGB);
end
```

GOES 12 Imagery of Hurricane Katrina Composited with NEXRAD Radar 2005-08-30T17:45:00Z



Close the Figure window and the AVI file.


```
close(fig)
close(writer)

Write the animated GIF file.

filename = fullfile(pwd,'wmsanimated.gif');
  if exist(filename,'file')
      delete(filename)
end
delayTime = 2.0;
loopCount = inf;
```

Step 11: View Animated GIF File

An animation can be viewed in the browser when the browser opens an animated GIF file.



Credits

Katrina Layer

The Katrina layer used in the example is from the NASA Goddard Space Flight Center's SVS Image Server and is maintained by the Scientific Visualization Studio.

For more information about this server, run:

```
>> wmsinfo('http://svs.gsfc.nasa.gov/cgi-bin/wms?')
```

NEXRAD Layer

The NEXRAD layer used in the example is from the Iowa State University's IEM WMS server and is a generated CONUS composite of National Weather Service (NWS) WSR-88D level III base reflectivity.

For more information about this server, run:

>> wmsinfo('http://mesonet.agron.iastate.edu/cgi-bin/wms/nexrad/n0r-t.cgi?')

See Also

wmsfind | refine | wmsupdate | wmsread | usamap | geoshow | WMSMapRequest | WebMapServer

Troubleshoot Common Problems with Web Maps

Why Does My Web Map Contain Empty Tiles?

If you create a web map and the display contains empty tiles, it can mean that the web map server is temporarily off line. To display web maps, the Mapping toolbox must create connections to web map providers over the Internet. Often, simply trying again after a few minutes solves the problem.

Why Does My Web Map Lose Detail When I Zoom In?

If you zoom in on a web map and certain details of the map disappear, it can mean that the map does not support that particular zoom level.

See Also

webmap

More About

• "Basic Workflow for Displaying Web Maps" on page 9-61

Mapping Applications

This chapter describes several types of numerical applications for geospatial data, including computing and spatial statistics, and calculating tracks, routes, and other information useful for solving navigation problems.

- "Geographic Statistics for Point Locations on a Sphere" on page 10-2
- "Equal-Areas in Geographic Statistics" on page 10-6
- "Navigation" on page 10-9
- "Fix Position" on page 10-11
- "Plan the Shortest Path" on page 10-20
- "Display Navigational Tracks" on page 10-23
- "Dead Reckoning" on page 10-26
- "Drift Correction" on page 10-30
- "Time Zones" on page 10-32

Geographic Statistics for Point Locations on a Sphere

Certain Mapping Toolbox functions compute basic geographical measures for spatial analysis and for filtering and conditioning data. Since MATLAB functions can compute statistics such as means, medians, and variances, why not use those functions in the toolbox? First of all, classical statistical formulas typically assume that data is one-dimensional (and, often, normally distributed). Because this is not true for geospatial data, spatial analysts have developed statistical measures that extend conventional statistics to higher dimensions.

Second, such formulas generally assume that data occupies a two-dimensional Cartesian coordinate system. Computing statistics for geospatial data with geographic coordinates as if it were in a Cartesian framework can give statistically inappropriate results. While this assumption can sometimes yield reasonable numerical approximations within small geographic regions, for larger areas it can lead to incorrect conclusions because of distance measures and area assumptions that are inappropriate for spheres and spheroids. Mapping Toolbox functions appropriately compute statistics for geospatial data, avoiding these potential pitfalls.

Geographic Means

Consider the problem of calculating the mean position of a collection of geographic points. Taking the arithmetical mean of the latitudes and longitudes using the standard MATLAB mean function may seem reasonable, but doing this could yield misleading results.

Take two points at the same latitude, 180° apart in longitude, for example $(30^{\circ}\text{N}, 90^{\circ}\text{W})$ and $(30^{\circ}\text{N}, 90^{\circ}\text{E})$. The *mean* latitude is (30+30)/2=30, which seems right. Similarly, the mean longitude must be (90+(-90))/2=0. However, as one can also express 90°W as 270°E , (90+270)/2=180 is also a valid mean longitude. Thus there are two correct answers, the prime meridian and the dateline. This demonstrates how the sphericity of the Earth introduces subtleties into spatial statistics.

This problem is further complicated when some points are at different latitudes. Because a degree of longitude at the Arctic Circle covers a much smaller distance than a degree at the equator, distance between points having a given difference in longitude varies by latitude.

Is in fact 30°N the right mean latitude in the first example? The mean position of two points should be equidistant from those two points, and should also minimize the total distance. Does (30°N,0°) satisfy these criteria?

```
dist1 = distance(30,90,30,0)
dist1 =
          75.5225
dist2 = distance(30,-90,30,0)
dist2 =
          75.5225
```

Consider a third point, (lat,lon), that is also equidistant from the above two points, but at a lesser distance:

```
dist1 = distance(30,90,lat,lon)
dist1 =
    60.0000
dist2 = distance(30,-90,lat,lon)
dist2 =
    60.0000
```

What is this mystery point? The lat is 90°N, and any lon will do. The North Pole is the true geographic mean of these two points. Note that the great circle containing both points runs through the North Pole (a great circle represents the shortest path between two points on a sphere).

The Mapping Toolbox function meanm determines the geographic mean of any number of points. It does this using three-dimensional vector addition of all the points. For example, try the following:

```
lats = [30 30];
longs = [-90 90];
[latbar,longbar] = meanm(lats,longs)
latbar =
     90
longbar =
     0
```

This is the answer you now expect. This geographic mean can result in one oddity; if the vectors all cancel each other, the mean is the center of the planet. In this case, the returned mean point is (NaN, NaN) and a warning is displayed. This phenomenon is highly improbable in real data, but can be easily constructed. For example, it occurs when all the points are equally spaced along a great circle. Try taking the geographic mean of $(0^{\circ},0^{\circ})$, $(0^{\circ},120^{\circ})$, and $(0^{\circ},240^{\circ})$, which trisect the equator.

```
elats = [0 0 0];
elons = [0 120 240];
meanm(elats,elons)
```

MATLAB issues a warning and returns a vector of NaN values.

Geographic Standard Deviation

As you might now expect, the Cartesian definition of standard deviation provided in the standard MATLAB function std is also inappropriate for geographic data that is unprojected or covers a significant portion of a planet. Depending upon your purpose, you might want to use the separate geographic deviations for latitude and longitude provided by the function stdm, or the single standard distance provided in stdist. Both methods measure the deviation of points from the mean position calculated by meanm.

The Meaning of stdm

The stdm function handles the latitude and longitude deviations separately.

```
[latstd,lonstd] = stdm(lat,lon)
```

The function returns two deviations, one for latitudes and one for longitudes.


Latitude deviation is a straightforward standard deviation calculation from the mean latitude (mean parallel) returned by meanm. This is a reasonable measure for most cases, since on a sphere at least, a degree of latitude always has the same arc length.

Longitude deviation is another matter. Simple calculations based on sum-of-squares angular deviation from the mean longitude (mean meridian) are misleading. The arc length represented by a degree of longitude at extreme latitudes is significantly smaller than that at low latitudes.

The term *departure* is used to represent the arc length distance along a parallel of a point from a given meridian. For example, assuming a spherical planet, the departure of a degree of longitude at the Equator is a degree of arc length, but the departure of a degree of longitude at a latitude of 60° is

one-half a degree of arc length. The ${\tt stdm}$ function calculates a sum-of-squares departure deviation from the mean meridian.

If you want to plot the one-sigma lines for stdm, the latitude sigma lines are parallels. However, the longitude sigma lines are not meridians; they are lines of constant departure from the mean parallel.




This handling of deviation has its problems. For example, its dependence upon the logic of the coordinate system can cause it to break down near the poles. For this reason, the standard distance provided by stdist is often a better measure of deviation. The stdm handling is useful for many applications, especially when the data is not global. For instance, these potential difficulties would not be a danger for data points confined to the country of Mexico.

The Meaning of stdist

The standard distance of geographic data is a measure of the dispersion of the data in terms of its distance from the geographic mean. Among its advantages are its applicability anywhere on the globe and its single value:

```
dist = stdist(lat,lon)
```

In short, the standard distance is the average, norm, or *cubic norm* of the distances of the data points in a great circle sense from the mean position. It is probably a superior measure to the two deviations returned by stdm except when a particularly latitude- or longitude-dependent feature is under examination.



See Also

More About

• "Equal-Areas in Geographic Statistics" on page 10-6

Equal-Areas in Geographic Statistics


A common error in applying two-dimensional statistics to geographic data lies in ignoring equal-area treatment. It is often necessary to *bin* data to statistically analyze it. In a Cartesian plane, this is easily done by dividing the space into equal *x-y* squares. The geographic equivalent of this is to bin up the data in equal latitude-longitude *squares*. Since such squares at high latitudes cover smaller areas than their low-latitude counterparts, the observations in these regions are underemphasized. The result can be conclusions that are biased toward the equator.

Geographic Histograms

The geographic histogram function histr allows you to display binned-up geographic observations. The histr function results in equirectangular binning. Each bin has the same angular measurement in both latitude and longitude, with a default measurement of 1 degree. The center latitudes and longitudes of the bins are returned, as well as the number of observations per bin:

[binlat,binlon,num] = histr(lats,lons)

As previously noted, these equirectangular bins result in counting bias toward the equator. Here is a display of the one-degree-by-one-degree binning of approximately 5,000 random data points in Russia. The relative size of the circles indicates the number of observations per bin:




This is a portion of the whole map, displayed in an equal-area Bonne projection. The first step in creating data displays without area bias is to choose an equal-area projection. The proportionally sized symbols are a result of the specialized display function scatterm.

You can eliminate the area bias by adding a fourth output argument to histr, that will be used to weight each bin's observation by that bin's area:

[binlat,binlon,num,wnum] = histr(lats,lons)

The fourth output is the weighted observation count. Each bin's observation count is divided by its normalized area. Therefore, a high-latitude bin will have a larger weighted number than a low-latitude bin with the same number of actual observations. The same data and bins look much different when they are area-weighted:



Notice that there are larger symbols to the north in this display. The previous display suggested that the data was relatively uniformly distributed. When equal-area considerations are included, it is clear that the data is skewed to the north. In fact, the data used is northerly skewed, but a simple equirectangular handling failed to demonstrate this.

The histr function, therefore, does provide for the display of area-weighted data. However, the actual bins used are of varying areas. Remember, the one-degree-by-one-degree bin near a pole is much smaller than its counterpart near the equator.

The hista function provides for actual equal-area bins.

Converting to an Equal-Area Coordinate System

The actual data itself can be converted to an equal-area coordinate system for analysis with other statistical functions. It is easy to convert a collection of geographic latitude-longitude points to an equal-area *x-y* Cartesian coordinate system. The grn2eqa function applies the same transformation used in calculating the Equal-Area Cylindrical projection:

$$[x,y] = grn2eqa(lat,lon)$$

For each geographic lat - lon pair, an equal-area x - y is returned. The variables x and y can then be operated on under the equal-area assumption, using a variety of two-dimensional statistical techniques. Tools for such analysis can be found in the Statistics and Machine Learning Toolbox software and elsewhere. The results can then be converted back to geographic coordinates using the eqa2grn function:

$$[lat,lon] = eqa2grn(x, y)$$

Remember, when converting back and forth between systems, latitude corresponds to y and longitude corresponds to x.

See Also

More About

"Geographic Statistics for Point Locations on a Sphere" on page 10-2 $\,$

Navigation

What Is Navigation?

Navigation is the process of planning, recording, and controlling the movement of a craft or vehicle from one location to another. The word derives from the Latin roots *navis* ("ship") and *agere* ("to move or direct"). Geographic information—usually in the form of latitudes and longitudes—is at the core of navigation practice. The toolbox includes specialized functions for navigating across expanses of the globe, for which projected coordinates are of limited use.

Navigating on land, over water, and through the air can involve a variety of tasks:

- Establishing position, using known, fixed landmarks (piloting)
- Using the stars, sun, and moon (celestial navigation)
- Using technology to fix positions (inertial guidance, radio beacons, and satellite navigation, including GPS)
- Deducing net movement from a past known position (dead reckoning)

Another navigational task involves planning a voyage or flight, which includes determining an efficient route (usually by great circle approximation), weather avoidance (optimal track routing), and setting out a plan of intended movement (track laydown). Mapping Toolbox functions support these navigational activities as well.

Conventions for Navigational Functions

Units

You can use and convert among several angular and distance measurement units. The navigational support functions are

- dreckon
- gcwaypts
- leas
- navfix

To make these functions easy to use, and to conform to common navigational practice, for these specific functions only, certain conventions are used:


- Angles are always in degrees.
- Distances are always in nautical miles.
- Speeds are always in knots (nautical miles per hour).

Related functions that *do not* carry this restriction include rhxrh, scxsc, gcxgc, gcxsc, track, timezone, and crossfix, because of their potential for application outside navigation.

Navigational Track Format

Navigational track format requires column-vector variables for the latitudes and longitudes of track waypoints. A *waypoint* is a point through which a track passes, usually corresponding to a course (or speed) change. Navigational tracks are made up of the line segments connecting these waypoints,

which are called legs. In this format, therefore, n legs are described using n+1 waypoints, because an endpoint for the final leg must be defined. Mapping Toolbox navigation functions always presume angle units are always given in degrees.



Here, five track legs require six waypoints. In navigational track format, the waypoints are represented by two 6-by-1 vectors, one for the latitudes and one for the longitudes.

See Also

More About

- "Fix Position" on page 10-11
- "Plan the Shortest Path" on page 10-20
- "Display Navigational Tracks" on page 10-23
- "Dead Reckoning" on page 10-26
- "Drift Correction" on page 10-30
- "Time Zones" on page 10-32

Fix Position

The fundamental objective of navigation is to determine at a given moment how to proceed to your destination, avoiding hazards on the way. The first step in accomplishing this is to establish your current position. Early sailors kept within sight of land to facilitate this. Today, navigation within sight (or radar range) of land is called *piloting*. Positions are fixed by correlating the bearings and/or ranges of landmarks. In real-life piloting, all sighting bearings are treated as rhumb lines, while in fact they are actually great circles.

Over the distances involved with visual sightings (up to 20 or 30 nautical miles), this assumption causes no measurable error and it provides the significant advantage of allowing the navigator to plot all bearings as straight lines on a Mercator projection.


The Mercator was designed exactly for this purpose. Range circles, which might be determined with a radar, are assumed to plot as true circles on a Mercator chart. This allows the navigator to manually draw the range arc with a compass.

These assumptions also lead to computationally efficient methods for fixing positions with a computer. The toolbox includes the navfix function, which mimics the manual plotting and fixing process using these assumptions.


To obtain a good navigational fix, your relationship to at least three known points is considered necessary. A questionable or poor fix can be obtained with two known points.

Some Possible Situations

In this imaginary coastal region, you take a visual bearing on the radio tower of 270°. At the same time, Gilligan's Lighthouse bears 0°. If you plot a 90°-270° line through the radio tower and a 0°-180° line through the lighthouse on your Mercator chart, the point at which the lines cross is a fix. Since you have used only two lines, however, its quality is questionable.



But wait; your port lookout says he took a bearing on Cape Jones of 300°. If that line exactly crosses the point of intersection of the first two lines, you will have a perfect fix.




Whoops. What happened? Is your lookout in error? Possibly, but perhaps one or both of your bearings was slightly in error. This happens all the time. Which point, 1, 2, or 3, is correct? As far as you know, they are all equally valid.

In practice, the little triangle is plotted, and the fix position is taken as either the center of the triangle or the vertex closest to a danger (like shoal water). If the triangle is large, the quality is reported as *poor*, or even as *no fix*. If a fourth line of bearing is available, it can be plotted to try to resolve the ambiguity. When all three lines appear to cross at exactly the same point, the quality is reported as *excellent* or *perfect*.


Notice that three lines resulted in three intersection points. Four lines would return six intersection points. This is a case of combinatorial counting. Each intersection corresponds to choosing two lines to intersect from among n lines.

The next time you traverse these straits, it is a very foggy morning. You can't see any landmarks, but luckily, your navigational radar is operating. Each of these landmarks has a good radar signature, so you're not worried. You get a range from the radio tower of 14 nautical miles and a range from the lighthouse of 15 nautical miles.



Now what? You took ranges from only two objects, and yet you have two possible positions. This ambiguity arises from the fact that circles can intersect twice.


Luckily, your radar watch reports that he has Cape Jones at 18 nautical miles. This should resolve everything.



You were lucky this time. The third range resolved the ambiguity and gave you an excellent fix. Three intersections practically coincide. Sometimes the ambiguity is resolved, but the fix is still poor because the three closest intersections form a sort of circular triangle.

Sometimes the third range only adds to the confusion, either by bisecting the original two choices, or by failing to intersect one or both of the other arcs at all. In general, when n arcs are used, 2x(n-choose-2) possible intersections result. In this example, it is easy to tell which ones are right.

Bearing lines and arcs can be combined. If instead of reporting a third range, your radar watch had reported a bearing from the radar tower of 20°, the ambiguity could also have been resolved. Note, however, that in practice, lines of bearing for navigational fixing should only be taken visually, except in desperation. A radar's beam width can be a degree or more, leading to uncertainty.



As you begin to wonder whether this manual plotting process could be automated, your first officer shows up on the bridge with a laptop and Mapping Toolbox software.

Using navfix

The navfix function can be used to determine the points of intersection among any number of lines and arcs. Be warned, however, that due to the combinatorial nature of this process, the computation time grows rapidly with the number of objects. To illustrate this function, assign positions to the landmarks. Point A, Cape Jones, is at (latA,lonA). Point B, the radio tower, is at (latB,lonB). Point C, Gilligan's Lighthouse, is at (latC,lonC).

For the bearing-lines-only example, the syntax is:

```
[latfix,lonfix] = navfix([latA latB latC],[lonA lonB lonC],...
[300 270 0])
```

This defines the three points and their bearings as taken *from the ship*. The outputs would look something like this, with actual numbers, of course:

```
latfix =
    latfix1
                  NaN
                                % A intersecting B
    latfix2
                  NaN
                                % A intersecting C
    latfix3
                                % B intersecting C
                  NaN
lonfix =
    lonfix1
                                % A intersecting B
                  NaN
    lonfix2
                  NaN
                                % A intersecting C
    lonfix3
                  NaN
                                % B intersecting C
```

Notice that these are two-column matrices. The second column consists of NaNs because it is used only for the two-intersection ambiguity associated with arcs.

For the range-arcs-only example, the syntax is

This defines the three points and their ranges as taken from the ship. The final argument indicates that the three cases are all ranges.

The outputs have the following form:

```
latfix =
  latfix11 latfix12 % A intersecting B
  latfix21 latfix22 % A intersecting C
  latfix31 latfix32 % B intersecting C

lonfix =
  lonfix11 lonfix12 % A intersecting B
  lonfix21 lonfix22 % A intersecting C
  lonfix31 lonfix32 % B intersecting C
```

Here, the second column is used, because each pair of arcs has two potential intersections.

For the bearings and ranges example, the syntax requires the final input to indicate which objects are lines of bearing (indicated with a 1) and which are range arcs (indicated with a 0):

```
[latfix,lonfix] = navfix([latB latB latC],[lonB lonB lonC],...
[20 14 15],[1 0 0])
```

The resulting output is mixed:

Only one intersection is returned for the line from B with the arc about B, since the line originates inside the circle and intersects it once. The same line intersects the other circle twice, and hence it returns two points. The two circles taken together also return two points.

Usually, you have an idea as to where you are before you take the fix. For example, you might have a dead reckoning position for the time of the fix (see below). If you provide navfix with this estimated position, it chooses from each pair of ambiguous intersections the point closest to the estimate. Here's what it might look like:

```
latfix =
    latfix11
                                % the only point
    latfix21
                                % the closer point
    latfix31
                                % the closer point
lonfix =
    lonfix11
                                % the only point
    lonfix21
                                % the closer point
    lonfix31
                                % the closer point
```

A Numerical Example of Using navfix


Define some specific points in the middle of the Atlantic Ocean. These are strictly arbitrary; perhaps they correspond to points in Atlantis:

```
lata = 3.1; lona = -56.2;
latb = 2.95; lonb = -55.9;
latc = 3.15; lonc = -55.95;
```

Plot them on a Mercator projection:

```
axesm('MapProjection','mercator','Frame','on',...
     'MapLatLimit', [2.8 3.3], 'MapLonLimit', [-56.3 -55.8])
plotm([lata latb latc],[lona lonb lonc],...
    'LineStyle','none','Marker','pentagram',...
'MarkerEdgeColor','b','MarkerFaceColor','b',...
     'MarkerSize',12)
```

Here is what it looks like (with labeling and imaginary coastlines added after the fact for illustration):




Take three visual bearings: Point A bears 289°, Point B bears 135°, and Point C bears 026.5°. Calculate the intersections:

```
[newlat,newlong] = navfix([lata latb latc],[lona lonb lonc],...
                           [289 135 26.5],[1 1 1])
newlat =
    3.0214
                 NaN
    3.0340
                 NaN
    3.0499
                 NaN
newlong =
    -55.9715
                   NaN
    -56.0079
                   NaN
    -56.0000
                   NaN
```

4 Add the intersection points to the map:

```
plotm(newlat,newlong,'LineStyle','none',...
    'Marker','diamond','MarkerEdgeColor','r',...
    'MarkerFaceColor','r','MarkerSize',9)
```




Bearing lines have been added to the map for illustration purposes. Notice that each pair of objects results in only one intersection, since all are lines of bearing.

What if instead, you had ranges from the three points, A, B, and C, of 13 nmi, 9 nmi, and 7.5 nmi, respectively?

```
[newlat,newlong] = navfix([lata latb latc],[lona lonb lonc],...
[13 9 7.5],[0 0 0])
newlat =
```

```
3.0739
             2.9434
   3.2413
             3.0329
   3.0443
             3.0880
newlong =
    -55.9846 -56.0501
    -56.0355 -55.9937
    -56.0168 -55.8413
```

Here's what these points look like:




Three of these points look reasonable, three do not.

What if, instead of a range from Point A, you had a bearing to it of 284°?

```
[newlat,newlong] = navfix([lata latb latc],[lona lonb lonc],...
                          [284 9 7.5],[1 0 0])
```

```
newlat =
   3.0526
             2.9892
   3.0592
             3.0295
   3.0443
             3.0880
newlong =
   -56.0096 -55.7550
   -56.0360 -55.9168
    -56.0168 -55.8413
```



Again, visual inspection of the results indicates which three of the six possible points seem like *reasonable* positions.

When using the dead reckoning position (3.05°N,56.0°W), the closer, more reasonable candidate from each pair of intersecting objects is chosen:

See Also

More About

- "Navigation" on page 10-9
- "Display Navigational Tracks" on page 10-23
- "Plan the Shortest Path" on page 10-20
- "Dead Reckoning" on page 10-26

Plan the Shortest Path

You know that the shortest path between two geographic points is a great circle. Sailors and aviators are interested in minimizing distance traveled, and hence time elapsed. You also know that the rhumb line is a path of constant heading, the *natural* means of traveling. In general, to follow a great circle path, you would have to continuously alter course. This is impractical. However, you can approximate a great circle path by rhumb line segments so that the added distance is minor and the number of course changes minimal.

Surprisingly, very few rhumb line track legs are required to closely approximate the distance of the great circle path.


Consider the voyage from Norfolk, Virginia (37°N,76°W), to Cape St. Vincent, Portugal (37°N,9°W), one of the most heavily trafficked routes in the Atlantic. A due-east rhumb line track is 3,213 nautical miles, while the optimal great circle distance is 3,141 nautical miles.

Although the rhumb line path is only a little more than 2% longer, this is an additional 72 miles over the course of the trip. For a 12-knot tanker, this results in a 6-hour delay, and in shipping, time is money. If just three rhumb line segments are used to approximate the great circle, the total distance of the trip is 3,147 nautical miles. Our tanker would suffer only a half-hour delay compared to a continuous rhumb line course. Here is the code for computing the three types of tracks between Norfolk and St. Vincent:

```
figure('color','w');
ha = axesm('mapproj','mercator',...
           'maplatlim',[25 55],'maplonlim',[-80 0]);
axis off, gridm on, framem on;
setm(ha, 'MLineLocation', 15, 'PLineLocation', 15);
mlabel on, plabel on;
load coastlines;
hg = geoshow(coastlat,coastlon,'displaytype','line','color','b');
% Define point locs for Norfolk, VA and St. Vincent, Portugal
norfolk = [37, -76];
stvincent = [37, -9];
geoshow(norfolk(1),norfolk(2),'DisplayType','point',...
    'markeredgecolor','k','markerfacecolor','k','marker','o')
text(-0.61,0.66,'Norfolk','HorizontalAlignment','left')
geoshow(stvincent(1), stvincent(2), 'DisplayType', 'point',...
    'markeredgecolor','k','markerfacecolor','k','marker','o')
text(0.54,0.66, 'St. Vincent', 'HorizontalAlignment', 'right')
% Compute and draw 100 points for great circle
gcpts = track2('gc',norfolk(1),norfolk(2),...
               stvincent(1),stvincent(2));
geoshow(gcpts(:,1),gcpts(:,2),'DisplayType','line',...
    'color', 'red', 'linestyle', '--')
text(-0.02,0.85, 'Great circle: 3,141 nm (optimal)',...
     color','r','HorizontalAlignment','center')
% Compute and draw 100 points for rhumb line
rhpts = track2('rh',norfolk(1),norfolk(2),...
                stvincent(1),stvincent(2));
geoshow(rhpts(:,1),rhpts(:,2),'DisplayType','line',...
     color',[.7 .1 0],'linestyle','-.')
text(-0.02,0.66, 'Direct course: 3,213 nm',...
```

```
'color',[.7 .1 0],'HorizontalAlignment','center')
% Compute and draw path along three waypoints
[latpts,lonpts] = gcwaypts(norfolk(1),norfolk(2),...
    stvincent(1),stvincent(2),3);
geoshow(latpts,lonpts,'DisplayType','line',...
    'color',[.4 .2 0],'linestyle','-')
text(-0.02,0.75,'3-leg approximation: 3,149 nm',...
    'color',[.4 .2 0],'HorizontalAlignment','center')
```

The resulting tracks and distances are shown below:



The Mapping Toolbox function <code>gcwaypts</code> calculates waypoints in navigation track format in order to approximate a great circle with rhumb line segments. It uses this syntax:

```
[latpts,lonpts] = gcwaypts(lat1,lon1,lat2,lon2,numlegs)
```

All the inputs for this function are scalars a (starting and an ending position). The numlegs input is the number of equal-length legs desired, which is 10 by default. The outputs are column vectors representing waypoints in navigational track format ([heading distance]). The size of each of these vectors is [(numlegs+1) 1]. Here are the points for this example:

These points represent waypoints along the great circle between which the approximating path follows rhumb lines. Four points are needed for three legs, because the final point at Cape St. Vincent must be included.

Now we can compute the distance in nautical miles (nm) along each track and via the waypoints:

```
drh = distance('rh',norfolk,stvincent); % Get rhumb line dist (deg)
dgc = distance('gc',norfolk,stvincent); % Get gt. circle dist (deg)
% Compute headings and distances for the waypoint legs
[course distnm] = legs(latpts,lonpts,'rh');
Finally, compare the distances:
distrhnm = deg2nm(drh)
                                        % Nautical mi along rhumb line
distgcnm = deg2nm(dgc)
                                        % Nautical mi along great circle
distgcnm = deg2nm(dgc) % Nautical mi along great circ
distlegsnm = sum(distnm) % Total dist along the 3 legs
rhgcdiff = distrhnm - distgcnm % Excess rhumb line distance
trgcdiff = distlegsnm - distgcnm % Excess distance along legs
distrhnm =
  3.2127e+003
distgcnm =
  3.1407e+003
distlegsnm =
  3.1490e+003
rhacdiff =
   71.9980
trgcdiff =
    8.3446
```

Following just three rhumb line legs reduces the distance travelled from 72 nm to 8.3 nm compared to a great circle course.

See Also

More About

- "Navigation" on page 10-9
- "Fix Position" on page 10-11
- "Display Navigational Tracks" on page 10-23
- "Dead Reckoning" on page 10-26

Display Navigational Tracks

Navigational tracks are most useful when graphically displayed. Traditionally, the navigator identifies and plots waypoints on a Mercator projection and then connects them with a straightedge, which on this projection results in rhumb line tracks. In the previous example, waypoints were chosen to approximate a great circle route, but they can be selected for a variety of other reasons.


Let's say that after arriving at Cape St. Vincent, your tanker must traverse the Straits of Gibraltar and then travel on to Port Said, the northern terminus of the Suez Canal. On the scale of the Mediterranean Sea, following great circle paths is of little concern compared to ensuring that the many straits and passages are safely transited. The navigator selects appropriate waypoints and plots them.

To accomplish this with Mapping Toolbox functions, you can display an <code>axesm</code>-based map with a Mercator projection, select appropriate map latitude and longitude limits to isolate the area of interest, plot coastline data, and interactively mouse-select the waypoints with the <code>inputm</code> function. The <code>track</code> function will generate points to connect these waypoints, which can then be displayed with <code>plotm</code>.

For illustration, assume that the waypoints are known (or were gathered using inputm). To learn about using inputm, see "Pick Locations Interactively" on page 4-85, or inputm in the Mapping Toolbox reference pages.

```
waypoints = [36 -5; 36 -2; 38 5; 38 11; 35 13; 33 30; 31.5 32]
waypoints =
    36.0000
              -5.0000
    36.0000
              -2.0000
    38.0000
              5.0000
    38.0000
              11.0000
    35.0000
              13.0000
              30.0000
    33.0000
    31.5000
              32.0000
load coastlines
axesm('MapProjection','mercator',...
'MapLatLimit',[30 47], 'MapLonLimit',[-10 37])
framem
plotm(coastlat,coastlon)
[lttrk,lntrk] = track(waypoints);
plotm(lttrk,lntrk,'r')
```

Although these track segments are straight lines on the Mercator projection, they are curves on others:



The segments of a track like this are called *legs*. Each of these legs can be described in terms of course and distance. The function legs will take the waypoints in navigational track format and return the course and distance required for each leg. Remember, the order of the points in this format determines the direction of travel. Courses are therefore calculated from each waypoint to its successor, not the reverse.

[courses, distances] = legs(waypoints)

```
courses =
    90.0000
    70.3132
    90.0000
    151.8186
    98.0776
    131.5684
distances =
    145.6231
    356.2117
    283.6839
    204.2073
    854.0092
    135.6415
```

Since this is a navigation function, the courses are all in degrees and the distances are in nautical miles. From these distances, speeds required to arrive at Port Said at a given time can be calculated. Southbound traffic is allowed to enter the canal only once per day, so this information might be economically significant, since unnecessarily high speeds can lead to high fuel costs.

See Also

More About


- "Navigation" on page 10-9
- "Fix Position" on page 10-11

- "Plan the Shortest Path" on page 10-20
- "Dead Reckoning" on page 10-26

Dead Reckoning

When sailors first ventured out of sight of land, they faced a daunting dilemma. How could they find their way home if they didn't know where they were? The practice of *dead reckoning* is an attempt to deal with this problem. The term is derived from *deduced reckoning*.

Briefly, dead reckoning is vector addition plotted on a chart. For example, if you have a fix at (30°N,10°W) at 0800, and you proceed due west for 1 hour at 10 knots, and then you turn north and sail for 3 hours at 7 knots, you should be at (30.35°N,10.19°W) at 1200.



However, a sailor *shoots the sun* at local apparent noon and discovers that the ship's latitude is actually 30.29°N. What's worse, he lives before the invention of a reliable chronometer, and so he cannot calculate his longitude at all from this sighting. What happened?

Leaving aside the difficulties in speed determination and the need to tack off course, even modern craft have to contend with winds and currents. However, despite these limitations, dead reckoning is still used for determining position between fixes and for forecasting future positions. This is because dead reckoning provides a certainty of assumptions that estimations of wind and current drift cannot.


When navigators establish a fix from some source, be it from piloting, celestial, or satellite observations, they plot a dead reckoning (DR) track, which is a plot of the intended positions of the ship forward in time. In practice, dead reckoning is usually plotted for 3 hours in advance, or for the time period covered by the next three expected fixes. In open ocean conditions, hourly fixes are sufficient; in coastal pilotage, three-minute fixes are common.

Specific DR positions, which are sometimes called *DR*s, are plotted according to the *Rules of DR*:

- DR at every course change
- DR at every speed change
- · DR every hour on the hour
- DR every time a fix or running fix is obtained

- DR 3 hours ahead or for the next three expected fixes
- DR for every line of position (LOP), either visual or celestial

For example, the navigator plots these DRs:



Notice that the 1523 DR does not coincide with the LOP at 1523. Although note is taken of this variance, one line is insufficient to calculate a new fix.

Mapping Toolbox function dreckon calculates the DR positions for a given set of courses and speeds. The function provides DR positions for the first three rules of dead reckoning. The approach is to provide a set of waypoints in navigational track format corresponding to the plan of intended movement.

The time of the initial waypoint, or fix, is also needed, as well as the speeds to be employed along each leg. Alternatively, a set of speeds and the times for which each speed will apply can be provided. dreckon returns the positions and times required of these DRs:

- dreckon calculates the times for position of each course change, which will occur at the waypoints
- dreckon calculates the positions for each whole hour
- If times are provided for speed changes, dreckon calculates positions for these times if they do not occur at course changes

Imagine you have a fix at midnight at the point $(10^{\circ}N,0^{\circ})$:

```
waypoints(1,:) = [10 \ 0]; fixtime = 0;
```


You intend to travel east and alter course at the point (10°N,0.13°E) and head for the point (10.1°N,0.18°E). On the first leg, you will travel at 5 knots, and on the second leg you will speed up to 7 knots.

```
waypoints(2,:) = [10 .13];
waypoints(3,:) = [10.1 .18];
speeds = [5;7];
```

To determine the DR points and times for this plan, use dreckon:

```
[drlat,drlon,drtime] = dreckon(waypoints,fixtime,speeds);
[drlat drlon drtime]
ans =
               0.0846
                                     % Position at 1 am
    10.0000
                         1.0000
    10.0000
               0.1301
                         1.5373
                                     % Time of course change
    10.0484
               0.1543
                         2.0000
                                     % Position at 2 am
    10.1001
               0.1801
                         2.4934
                                     % Time at final waypoint
```

Here is an illustration of this track and its DR points:




However, you would like to get to the final point a little earlier to make a rendezvous. You decide to recalculate your DRs based on speeding up to 7 knots a little earlier than planned. The first calculation tells you that you were going to increase speed at the turn, which would occur at a time 1.5373 hours after midnight, or 1:32 a.m. (at time 0132 in navigational time format). What time would you reach the rendezvous if you increased your speed to 7 knots at 1:15 a.m. (0115, or 1.25 hours after midnight)?

To indicate times for speed changes, another input is required, providing a time interval after the fix time at which each ordered speed is to end. The first speed, 5 knots, is to end 1.25 hours after midnight. Since you don't know when the rendezvous will be made under these circumstances, set the time for the second speed, 7 knots, to end at infinity. No DRs will be returned past the last waypoint.

```
spdtimes = [1.25; inf];
[drlat,drlon,drtime] = dreckon(waypoints,fixtime,...
                                speeds, spdtimes);
[drlat,drlon,drtime]
ans =
    10.0000
                                   % Position at 1 am
               0.0846
                         1.0000
                          1.2500
    10.0000
               0.1058
                                   % Position at speed change
    10.0000
               0.1301
                         1.4552
                                   % Time of course change
    10.0570
               0.1586
                          2.0000
                                   % Position at 2 am
    10.1001
               0.1801
                         2.4113
                                   % Time at final waypoint
```

This following illustration shows the difference:



The times at planned positions after the speed change are a little earlier; the position at the known time (2 a.m.) is a little farther along. With this plan, you will arrive at the rendezvous about 4 1/2 minutes earlier, so you may want to consider a greater speed change.

See Also


More About

- "Navigation" on page 10-9
- "Fix Position" on page 10-11
- "Plan the Shortest Path" on page 10-20
- "Display Navigational Tracks" on page 10-23
- "Drift Correction" on page 10-30

Drift Correction

Dead reckoning is a reasonably accurate method for predicting position if the vehicle is able to maintain the planned course. Aircraft and ships can be pushed off the planned course by winds and current. An important step in navigational planning is to calculate the required drift correction.

In the standard drift correction problem, the desired course and wind are known, but the heading needed to stay on course is unknown. This problem is well suited to vector analysis. The wind velocity is a vector of known magnitude and direction. The vehicle's speed relative to the moving air mass is a vector of known magnitude, but unknown direction. This heading must be chosen so that the sum of the vehicle and wind velocities gives a resultant in the specified course direction. The ground speed can be larger or smaller than the air speed because of headwind or tailwind components. A navigator would like to know the required heading, the associated wind correction angle, and the resulting ground speed.



What heading puts an aircraft on a course of 250° when the wind is 38 knots from 285°? The aircraft flies at an airspeed of 145 knots.

The required heading is about 9° to the right of the course. There is a 33-knot headwind component.

A related problem is the calculation of the wind speed and direction from observed heading and course. The wind velocity is just the vector difference of the ground speed and the velocity relative to the air mass.

See Also

More About


- "Navigation" on page 10-9
- "Fix Position" on page 10-11
- "Plan the Shortest Path" on page 10-20
- "Display Navigational Tracks" on page 10-23
- "Dead Reckoning" on page 10-26

Time Zones

Time zones used for navigation are uniform 15° extents of longitude. The timezone function returns a navigational time zone, that is, one based solely on longitude with no regard for statutory divisions. So, for example, Chicago, Illinois, lies in the statutory U.S. Central time zone, which has irregular boundaries devised for political or convenience reasons. However, from a navigational standpoint, Chicago's longitude places it in the S (Sierra) time zone. The zone's *description* is +6, which indicates that 6 hours must be added to local time to get Greenwich, or Z (Zulu) time. So, if it is noon, standard time in Chicago, it is 12+6, or 6 p.m., at Greenwich.

Each 15° navigational time zone has a distinct description and designating letter. The exceptions to this are the two zones on either side of the date line, M and Y (Mike and Yankee). These zones are only 7-1/2° wide, since on one side of the date line, the description is +12, and on the other, it is -12.

Navigational time zones are very important for celestial navigation calculations. Although there are no Mapping Toolbox functions designed specifically for celestial navigation, a simple example can be devised.



It is possible with a sextant to determine *local apparent noon*. This is the moment when the Sun is at its zenith from your point of view. At the exact center longitude of a time zone, the phenomenon occurs exactly at noon, local time. Since the Sun traverses a 15° time zone in 1 hour, it crosses one degree every 4 minutes. So if you observe local apparent noon at 11:54, you must be 1.5° east of your center longitude.

You must know what time zone you are in before you can even attempt a fix. This concept has been understood since the spherical nature of the Earth was first accepted, but early sailors had no ability to keep accurate time on ship, and so were unable to determine their longitude. The invention of accurate chronometers in the 18th century solved this problem.

The timezone function is quite simple. It returns zd, an integer for use in calculations, zltr, a character vector of the zone designator, and zone, a character vector fully naming the zone. For example, the information for a longitude 123°E is the following:

```
[zd,zltr,zone] = timezone(123)
zd =
    -8
zltr =
    H
zone =
    -8 H
```

Returning to the simple celestial navigation example, the center longitude of this zone is:

```
-(zd*15)
ans =
```

This means that at our longitude, 123°E, we should experience local apparent noon at 11:48 a.m., 12 minutes early.

See Also

More About

• "Navigation" on page 10-9

Map Projections — Alphabetical List

aitoff

Aitoff projection

Classification

Modified Azimuthal

Identifier

aitoff

Graticule

Meridians: Central meridian is a straight line half the length of the Equator. Other meridians are complex curves, equally spaced along the Equator, and concave toward the central meridian.

Parallels: Equator is straight. Other parallels are complex curves, equally spaced along the central meridian, and concave toward the nearest pole.

Poles: Points.

Symmetry: About the Equator and central meridian.

Features

This projection is neither conformal nor equal area. The only point free of distortion is the center point. Distortion of shape and area are moderate throughout. This projection has less angular distortion on the outer meridians near the poles than pseudoazimuthal projections

Parallels


There is no standard parallel for this projection.

Remarks

- This projection was created by David Aitoff in 1889. It is a modification of the Equidistant Azimuthal projection. The Aitoff projection inspired the similar Hammer projection, which is equal area.
- This implementation of the Aitoff projection is applicable only for coordinates that are referenced to a sphere. If you want to project coordinates that are referenced to an ellipsoid, using the projfwd or projinv functions, then create a projcrs object instead of a map projection structure. You can create a projers object for the Aitoff projection using the ESRI authority code 54043. For example: projcrs(54043, 'Authority', 'ESRI').

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('aitoff', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History

Introduced before R2006a

egaconic

Albers Equal-Area Conic Projection

Classification

Conic

Identifier

egaconic

Graticule

Meridians: Equally spaced straight lines converging to a common point, usually beyond the pole. The angles between the meridians are less than the true angles.

Parallels: Unequally spaced concentric circular arcs centered on the point of convergence. Spacing of parallels decreases away from the central latitudes.

Poles: Normally circular arcs, enclosing the same angle as the displayed parallels.

Symmetry: About any meridian.

Features

This is an equal-area projection. Scale is true along the one or two selected standard parallels. Scale is constant along any parallel; the scale factor of a meridian at any given point is the reciprocal of that along the parallel to preserve equal-area. This projection is free of distortion along the standard parallels. Distortion is constant along any other parallel. This projection is neither conformal nor equidistant.

Parallels

The cone of projection has interesting limiting forms. If a pole is selected as a single standard parallel, the cone is a plane and a Lambert Azimuthal Equal-Area projection results. If two parallels are chosen, not symmetric about the Equator, then a Lambert Equal-Area Conic projection results. If a pole is selected as one of the standard parallels, then the projected pole is a point, otherwise the projected pole is an arc. If the Equator is chosen as a single parallel, the cone becomes a cylinder and a Lambert Equal-Area Cylindrical projection is the result. Finally, if two parallels equidistant from the Equator are chosen as the standard parallels, a Behrmann or other equal-area cylindrical projection is the result. Suggested parallels for maps of the conterminous U.S. are [29.5 45.5]. The default parallels are [15 75].

Remarks


This projection was presented by Heinrich Christian Albers in 1805.

Limitations

Longitude data greater than 135° east or west of the central meridian is trimmed.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('eqaconic', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



See Also

eqaconicstd on page 11-6

Version History

Introduced before R2006a

egaconicstd

Albers Equal-Area Conic Projection — Standard

Classification

Conic

Identifier

egaconicstd

Graticule

Meridians: Equally spaced straight lines converging to a common point, usually beyond the pole. The angles between the meridians are less than the true angles.

Parallels: Unequally spaced concentric circular arcs centered on the point of convergence. Spacing of parallels decreases away from the central latitudes.

Poles: Normally circular arcs, enclosing the same angle as the displayed parallels.

Symmetry: About any meridian.

Features

This function implements the Albers Equal Area Conic projection directly on a reference ellipsoid, consistent with the industry-standard definition of this projection. See egaconic on page 11-4 for an alternative implementation based on rotating the authalic sphere.

This is an equal area projection. Scale is true along the one or two selected standard parallels. Scale is constant along any parallel; the scale factor of a meridian at any given point is the reciprocal of that along the parallel to preserve equal area. The projection is free of distortion along the standard parallels. Distortion is constant along any other parallel. This projection is neither conformal nor equidistant.

Parallels


The cone of projection has interesting limiting forms. If a pole is selected as a single standard parallel, the cone is a plane and a Lambert Azimuthal Equal-Area projection results. If two parallels are chosen, not symmetric about the Equator, then a Lambert Equal-Area Conic projection results. If a pole is selected as one of the standard parallels, then the projected pole is a point, otherwise the projected pole is an arc. If the Equator is chosen as a single parallel, the cone becomes a cylinder and a Lambert Equal-Area Cylindrical projection is the result. Finally, if two parallels equidistant from the Equator are chosen as the standard parallels, a Behrmann or other equal-area cylindrical projection is the result. Suggested parallels for maps of the conterminous U.S. are [29.5 45.5]. The default parallels are [15 75].

Remarks

- This projection was presented by Heinrich Christian Albers in 1805 and it is also known as a Conical Orthomorphic projection. The cone of projection has interesting limiting forms. If a pole is selected as a single standard parallel, the cone is a plane, and a Lambert Equal Area Conic projection is the result. If the Equator is chosen as a single parallel, the cone becomes a cylinder and a Lambert Cylindrical Equal Area Projection is the result. Finally, if two parallels equidistant from the Equator are chosen as the standard parallels, a Behrmann or other cylindrical equal area projection is the result.
- Mapping Toolbox uses a different implementation of the standard Albers equal-area conic projection for displaying coordinates on axesm-based maps than for projecting coordinates using the projfwd or projinv function. These implementations may produce differing results.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('eqaconicstd', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



See also

egaconic on page 11-4

Version History

Introduced before R2006a

apianus

Apianus II Projection

Classification

Pseudocylindrical

Identifier

apianus

Graticule

Meridians: Equally spaced elliptical curves converging at the poles.

Parallels: Equally spaced straight lines.

Poles: Points.

Symmetry: About the Equator and central meridian.

Features

Scale is constant along any parallel or pair of parallels equidistant from the Equator, as well as along the central meridian. The Equator is free of angular distortion. This projection is not equal-area, equidistant, or conformal.

Parallels


There is no standard parallel for this projection.

Remarks

- This projection was first described in 1524 by Peter Apian (or Bienewitz).
- This implementation of the Apianus II projection is applicable only for coordinates that are referenced to a sphere.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('apianus', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

balthsrt

Balthasart Cylindrical Projection

Classification

Cylindrical

Identifier

balthsrt

Graticule

Meridians: Equally spaced straight parallel lines.

Parallels: Unequally spaced straight parallel lines, perpendicular to the meridians. Spacing is closest near the poles.

Poles: Straight lines equal in length to the Equator.

Symmetry: About any meridian or the Equator.

Features

This is an orthographic projection onto a cylinder secant at the 50° parallels. It is equal-area, but distortion of shape increases with distance from the standard parallels. Scale is true along the standard parallels and constant between two parallels equidistant from the Equator. This projection is not equidistant.

Standard Parallels


For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, the standard parallel is by definition fixed at 50º.

Remarks

The Balthasart Cylindrical projection was presented in 1935 and is a special form of the Equal-Area Cylindrical projection secant at 50°N and S.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('balthsrt', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

behrmann

Behrmann Cylindrical Projection

Classification

Cylindrical

Identifier

behrmann

Graticule

Meridians: Equally spaced straight parallel lines 0.42 as long as the Equator.

Parallels: Unequally spaced straight parallel lines, perpendicular to the meridians. Spacing is closest near the poles.

Poles: Straight lines equal in length to the Equator.

Symmetry: About any meridian or the Equator.

Features

This is an orthographic projection onto a cylinder secant at the 30° parallels. It is equal-area, but distortion of shape increases with distance from the standard parallels. Scale is true along the standard parallels and constant between two parallels equidistant from the Equator. This projection is not equidistant.

Parallels


For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, the standard parallel is by definition fixed at 30º.

Remarks

This projection is named for Walter Behrmann, who presented it in 1910 and is a special form of the Equal-Area Cylindrical projection secant at 30°N and S.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('behrmann', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

bsam

Bolshoi Sovietskii Atlas Mira Projection

Classification

Cylindrical

Identifier

bsam

Graticule

Meridians: Equally spaced straight parallel lines.

Parallels: Unequally spaced straight parallel lines, perpendicular to the meridians. Spacing increases toward the poles.

Poles: Straight lines equal in length to the Equator.

Symmetry: About any meridian or the Equator.

Features

This is a perspective projection from a point on the Equator opposite a given meridian onto a cylinder secant at the 30° parallels. It is not equal-area, equidistant, or conformal. Scale is true along the standard parallels and constant between two parallels equidistant from the Equator. There is no distortion along the standard parallels, but it increases moderately away from these parallels, becoming severe at the poles.

Parallels


For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, the standard parallel is by definition fixed at 30º.

Remarks

- This projection was first described in 1937, when it was used for maps in the Bolshoi Sovietskii Atlas Mira (Great Soviet World Atlas). It is commonly abbreviated as the BSAM projection. It is a special form of the Braun Perspective Cylindrical projection secant at 30°N and S.
- This implementation of the Bolshoi Sovietskii Atlas Mira projection is applicable only for coordinates that are referenced to a sphere.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('bsam', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History

Introduced before R2006a

bonne

Bonne Projection

Classification

Pseudoconic

Identifier

bonne

Graticule

Central Meridian: A straight line.

Meridians: Complex curves connecting points equally spaced along each parallel and concave toward the central meridian.

Parallels: Concentric circular arcs spaced at true distances along the central meridian.

Poles: Points.

Symmetry: About the central meridian.

Features

This is an equal-area projection. The curvature of the standard parallel is identical to that on a cone tangent at that latitude. The central meridian and the central parallel are free of distortion. This projection is not conformal.

Parallels

This projection has one standard parallel, which is $30^{\circ}N$ by default. It has two interesting limiting forms. If a pole is employed as the standard parallel, a Werner projection results; if the Equator is used, a Sinusoidal projection results.


Remarks

This projection dates in a rudimentary form back to Claudius Ptolemy (about A.D. 100). It was further developed by Bernardus Sylvanus in 1511. It derives its name from its considerable use by Rigobert Bonne, especially in 1752.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('bonne', 'Frame', 'on', 'Grid', 'on');
```

geoshow(landareas, 'FaceColor',[1 1 .5], 'EdgeColor',[.6 .6 .6]);
tissot;



Version History Introduced before R2006a

braun

Braun Perspective Cylindrical Projection

Classification

Cvlindrical

Identifier

braun

Graticule

Meridians: Equally spaced straight parallel lines.

Parallels: Unequally spaced straight parallel lines, perpendicular to the meridians. Spacing increases toward the poles.

Poles: Straight lines equal in length to the Equator.

Symmetry: About any meridian or the Equator.

Features

This is an perspective projection from a point on the Equator opposite a given meridian onto a cylinder secant at standard parallels. It is not equal-area, equidistant, or conformal. Scale is true along the standard parallels and constant between two parallels equidistant from the Equator. There is no distortion along the standard parallels, but it increases moderately away from these parallels, becoming severe at the poles.

Parallels

For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, any latitude may be chosen; the default is arbitrarily set to 0° .


Remarks

- This projection was first described by Braun in 1867. It is less well known than the specific forms of it called the Gall Stereographic and the Bolshoi Sovietskii Atlas Mira projections.
- This implementation of the Braun perspective cylindrical projection is applicable only for coordinates that are referenced to a sphere.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('braun', 'Frame', 'on', 'Grid', 'on');
```

geoshow(landareas, 'FaceColor',[1 1 .5], 'EdgeColor',[.6 .6 .6]);
tissot;



Version History Introduced before R2006a

breusing

Breusing Harmonic Mean Projection

Classification

Azimuthal

Identifier

breusing

Graticule

The graticule described is for the polar aspect.

Meridians: Equally spaced straight lines intersecting at the central pole.

Parallels: Unequally spaced circles centered on the central pole. The opposite hemisphere cannot be shown. Spacing increases (slightly) away from the central pole.

Poles: The central pole is a point, while the opposite pole cannot be shown.

Symmetry: About any meridian.

Features

This is a harmonic mean between a Stereographic and Lambert Equal-Area Azimuthal projection. It is not equal-area, equidistant, or conformal. There is no point at which scale is accurate in all directions. The primary feature of this projection is that it is minimum error—distortion is moderate throughout.


Parallels

There are no standard parallels for azimuthal projections.

Remarks

- F. A. Arthur Breusing developed a geometric mean version of this projection in 1892. A. E. Young modified this to the harmonic mean version presented here in 1920. This projection is virtually indistinguishable from the Airy Minimum Error Azimuthal projection, presented by George Airy in 1861.
- This implementation of the Breusing harmonic mean projection is applicable only for coordinates that are referenced to a sphere.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('breusing', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History

bries

Briesemeister Projection

Classification

Modified Azimuthal

Identifier

bries

Graticule

Meridians: Central meridian is straight. Other meridians are complex curves.

Parallels: Complex curves.

Poles: Points.

Symmetry: About the central meridian.

Features

This equal-area projection groups the continents about the center of the projection. The only point free of distortion is the center point. Distortion of shape and area are moderate throughout.


Parallels

There is no standard parallel for this projection.

Remarks

- This projection was presented by William Briesemeister in 1953. It is an oblique Hammer projection with an axis ratio of 1.75 to 1, instead of 2 to 1.
- This implementation of the Briesemeister projection is applicable only for coordinates that are referenced to a sphere.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('bries', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

cassini

Cassini Cylindrical Projection

Classification

Cylindrical

Identifier

cassini

Graticule

Central Meridian: Straight line (includes meridian opposite the central meridian in one continuous line).

Other Meridians: Straight lines if 90° from central meridian, complex curves concave toward the central meridian otherwise.

Parallels: Complex curves concave toward the nearest pole.

Poles: Points along the central meridian.

Symmetry: About any straight meridian or the Equator.

Features


This is a projection onto a cylinder tangent at the central meridian. Distortion of both shape and area are functions of distance from the central meridian. Scale is true along the central meridian and along any straight line perpendicular to the central meridian (i.e., it is equidistant).

Parallels

For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, the standard parallel of the base projection is by definition fixed at 0° .

- This projection is the transverse aspect of the Plate Carrée projection, developed by César François Cassini de Thury (1714-1784). It is still used for the topographic mapping of a few countries.
- This implementation of the Cassini cylindrical projection is applicable only for coordinates that are referenced to a sphere.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('cassini', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



See also

cassinistd on page 11-26

Version History

cassinistd

Cassini Cylindrical Projection — Standard

Identifier

cassinistd

Graticule

Central Meridian: Straight line (includes meridian opposite the central meridian in one continuous line).

Other Meridians: Straight lines if 90° from central meridian, complex curves concave toward the central meridian otherwise.

Parallels: Complex curves concave toward the nearest pole.

Poles: Points along the central meridian.

Symmetry: About any straight meridian or the Equator.

Features


This is a projection onto a cylinder tangent at the central meridian. Distortion of both shape and area are functions of distance from the central meridian. Scale is true along the central meridian and along any straight line perpendicular to the central meridian (i.e., it is equidistant).

Parallels

For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, the standard parallel of the base projection is by definition fixed at 0° .

- This projection is the transverse aspect of the Plate Carrée projection, developed by César François Cassini de Thury (1714-1784). It is still used for the topographic mapping of a few countries.
- cassinistd implements the Cassini projection directly on a sphere or reference ellipsoid, as opposed to using the equidistant cylindrical projection in transverse mode as in function cassini on page 11-24. Distinct forms are used for the sphere and ellipsoid, because approximations in the ellipsoidal formulation cause it to be appropriate only within a zone that extends 3 or 4 degrees in longitude on either side of the central meridian.
- Mapping Toolbox uses a different implementation of the standard Cassini cylindrical projection for displaying coordinates on axesm-based maps than for projecting coordinates using the projfwd or projiny function. These implementations may produce differing results.

landareas = shaperead('landareas.shp', 'UseGeoCoords',true);
axesm ('cassinistd', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor',[1 1 .5], 'EdgeColor',[.6 .6 .6]);
tissot;



See also

cassini on page 11-24

Version History

ccylin

Central Cylindrical Projection

Classification

Cylindrical

Identifier

ccylin

Graticule

Meridians: Equally spaced straight parallel lines.

Parallels: Unequally spaced straight parallel lines, perpendicular to the meridians. Spacing increases toward the poles, more rapidly than that of the Mercator projection.

Poles: Cannot be shown.

Symmetry: About any meridian or the Equator.

Features

This is a perspective projection from the center of the Earth onto a cylinder tangent at the Equator. It is not equal-area, equidistant, or conformal. Scale is true along the Equator and constant between two parallels equidistant from the Equator. Scale becomes infinite at the poles. There is no distortion along the Equator, but it increases rapidly away from the Equator.

Parallels

For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, the standard parallel is by definition fixed at 0º.


Remarks

- The origin of this projection is unknown; it has little use beyond the educational aspects of its method of projection and as a comparison to the Mercator projection, which is not perspective. The transverse aspect of the central cylindrical is called the Wetch projection.
- This implementation of the central cylindrical projection is applicable only for coordinates that are referenced to a sphere.

Limitations

Data at latitudes greater than 75° is trimmed to prevent large values from dominating the display.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('ccylin', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History

collig

Collignon Projection

Classification

Pseudocylindrical

Identifier

collig

Graticule

Meridians: Equally spaced straight lines converging at the North Pole.

Parallels: Unequally spaced straight parallel lines, farthest apart near the North Pole, closest near the South Pole

Poles: North Pole is a point, South Pole is a line 1.41 as long as the Equator.

Symmetry: About the central meridian.

Features

This is a novelty projection showing a straight-line, equal-area graticule. Scale is true along the 15°51'N parallel, constant along any parallel, and different for any pair of parallels. Distortion is severe in many regions, and is only absent at 15°51'N on the central meridian. This projection is not conformal or equidistant.


Parallels

This projection has one standard parallel, which is by definition fixed at 15°51'.

Remarks

This projection was presented by Édouard Collignon in 1865.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('collig', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

craster

Craster Parabolic Projection

Classification

Pseudocylindrical

Identifier

craster

Graticule

Central Meridian: Straight line half as long as the Equator.

Other Meridians: Equally spaced parabolas intersecting at the poles and concave toward the central meridian.

Parallels: Unequally spaced straight parallel lines, perpendicular to the central meridian. Spacing changes very gradually and is greatest near the Equator.

Poles: Points.

Symmetry: About the central meridian or the Equator.

Features

This is an equal-area projection. Scale is true along the $36^{\circ}46'$ parallels and is constant along any parallel and between any pair of parallels equidistant from the Equator. Distortion is severe near the outer meridians at high latitudes, but less so than the Sinusoidal projection. This projection is free of distortion only at the two points where the central meridian intersects the 36°46' parallels. This projection is not conformal or equidistant.

Parallels


For this projection, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. The standard parallel is by definition fixed at 36°46'.

Remarks

This projection was developed by John Evelyn Edmund Craster in 1929; it was further developed by Charles H. Deetz and O.S. Adams in 1934. It was presented independently in 1934 by Putnins as his P₄ projection.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('craster', 'Frame', 'on', 'Grid', 'on');
```

geoshow(landareas, 'FaceColor',[1 1 .5], 'EdgeColor',[.6 .6 .6]);
tissot;



Version History Introduced before R2006a

eckert1

Eckert I Projection

Classification

Pseudocylindrical

Identifier

eckert1

Graticule

Central Meridian: Straight line half as long as the Equator.

Other Meridians: Equally spaced straight converging lines broken at the Equator.

Parallels: Equally spaced straight parallel lines, perpendicular to the central meridian.

Poles: Lines half as long as the Equator.

Symmetry: About the central meridian or the Equator.

Features


Scale is true along the 47°10' parallels and is constant along any parallel, between any pair of parallels equidistant from the Equator, and along any given meridian. It is not free of distortion at any point, and the break at the Equator introduces excessive distortion there; regardless of the appearance here, the Tissot indicatrices are of indeterminate shape along the Equator. This novelty projection is not equal-area or conformal.

Parallels

For this projection, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. The standard parallel is by definition fixed at 47°10'.

- This projection was presented by Max Eckert in 1906.
- This implementation of the Eckert I projection is applicable only for coordinates that are referenced to a sphere. If you want to project coordinates that are referenced to an ellipsoid, using the projfwd or projinv functions, then create a projers object instead of a map projection structure. You can create a projers object for the Eckert I projection using the ESRI authority code 54015. For example: projcrs(54015, 'Authority', 'ESRI').

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('eckert1', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History

eckert2

Eckert ll Projection

Classification

Pseudocylindrical

Identifier

eckert2

Graticule

Central Meridian: Straight line half as long as the Equator.

Other Meridians: Equally spaced straight converging lines broken at the Equator.

Parallels: Unequally spaced straight parallel lines, perpendicular to the central meridian. Spacing is widest near the Equator.

Poles: Lines half as long as the Equator.

Symmetry: About the central meridian or the Equator.

Features

This is an equal-area projection. Scale is true along the $55^{\circ}10'$ parallels and is constant along any parallel and between any pair of parallels equidistant from the Equator. It is not free of distortion at any point except at 55°10'N and S along the central meridian; the break at the Equator introduces excessive distortion there. Regardless of the appearance here, the Tissot indicatrices are of indeterminate shape along the Equator. This novelty projection is not conformal or equidistant.


Parallels

For this projection, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. The standard parallel is by definition fixed at 55°10'.

Remarks

This projection was presented by Max Eckert in 1906.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('eckert2', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

eckert3

Eckert Ill Projection

Classification

Pseudocylindrical

Identifier

eckert3

Graticule

Central Meridian: Straight line half as long as the Equator.

Other Meridians: Equally spaced semiellipses concave toward the central meridian. The outer meridians, 180º east and west of the central meridian, are semicircles.

Parallels: Equally spaced straight parallel lines, perpendicular to the central meridian.

Poles: Lines half as long as the Equator.

Symmetry: About the central meridian or the Equator.

Features


Scale is true along the 35°58' parallels and is constant along any parallel and between any pair of parallels equidistant from the Equator. No point is free of all scale distortion, but the Equator is free of angular distortion. This projection is not equal-area, conformal, or equidistant.

Parallels

For this projection, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. The standard parallel is by definition fixed at 35°58'.

- This projection was presented by Max Eckert in 1906.
- This implementation of the Eckert III projection is applicable only for coordinates that are referenced to a sphere. If you want to project coordinates that are referenced to an ellipsoid, using the projfwd or projinv functions, then create a projers object instead of a map projection structure. You can create a projers object for the Eckert III projection using the ESRI authority code 54013. For example: projcrs (54013, 'Authority', 'ESRI').

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('eckert3', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History

eckert4

Eckert IV Projection

Classification

Pseudocylindrical

Identifier

eckert4

Graticule

Central Meridian: Straight line half as long as the Equator.

Other Meridians: Equally spaced semiellipses concave toward the central meridian. The outer meridians, 180º east and west of the central meridian, are semicircles.

Parallels: Unequally spaced straight parallel lines, perpendicular to the central meridian. Spacing is greatest toward the Equator.

Poles: Lines half as long as the Equator.

Symmetry: About the central meridian or the Equator.

Features

This is an equal-area projection. Scale is true along the $40^{\circ}30'$ parallels and is constant along any parallel and between any pair of parallels equidistant from the Equator. It is free of distortion only at the two points where the $40^{\circ}30'$ parallels intersect the central meridian. This projection is not conformal or equidistant.


Parallels

For this projection, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. The standard parallel is by definition fixed at 40°30'.

Remarks

This projection was presented by Max Eckert in 1906.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('eckert4', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

eckert5

Eckert V Projection

Classification

Pseudocylindrical

Identifier

eckert5

Graticule

Central Meridian: Straight line half as long as the Equator.

Other Meridians: Equally spaced sinusoidal curves concave toward the central meridian.

Parallels: Equally spaced straight parallel lines, perpendicular to the central meridian.

Poles: Lines half as long as the Equator.

Symmetry: About the central meridian or the Equator.

Features

This projection is an arithmetic average of the x and y coordinates of the Sinusoidal and Plate Carrée projections. Scale is true along latitudes 37°55'N and S, and is constant along any parallel and between any pair of parallels equidistant from the Equator. There is no point free of all distortion, but the Equator is free of angular distortion. This projection is not equal-area, conformal, or equidistant.

Parallels


This projection has one standard parallel, which is by definition fixed at 0° .

Remarks

- This projection was presented by Max Eckert in 1906.
- This implementation of the Eckert V projection is applicable only for coordinates that are referenced to a sphere. If you want to project coordinates that are referenced to an ellipsoid, using the projfwd or projinv functions, then create a projers object instead of a map projection structure. You can create a projers object for the Eckert V projection using the ESRI authority code 54011. For example: projcrs (54011, 'Authority', 'ESRI').

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('eckert5', 'Frame', 'on', 'Grid', 'on');
```

geoshow(landareas, 'FaceColor',[1 1 .5], 'EdgeColor',[.6 .6 .6]);
tissot;



Version History Introduced before R2006a

eckert6

Eckert VI Projection

Classification

Pseudocylindrical

Identifier

eckert6

Graticule

Central Meridian: Straight line half as long as the Equator.

Other Meridians: Equally spaced sinusoidal curves concave toward the central meridian.

Parallels: Unequally spaced straight parallel lines, perpendicular to the central meridian. Spacing is greatest toward the Equator.

Poles: Lines half as long as the Equator.

Symmetry: About the central meridian or the Equator.

Features

This is an equal-area projection. Scale is true along the $49^{\circ}16'$ parallels and is constant along any parallel and between any pair of parallels equidistant from the Equator. It is free of distortion only at the two points where the $49^{\circ}16'$ parallels intersect the central meridian. This projection is not conformal or equidistant.


Parallels

For this projection, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. The standard parallel is by definition fixed at 49º16'.

Remarks

This projection was presented by Max Eckert in 1906.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('eckert6', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

egacylin

Equal-Area Cylindrical Projection

Classification

Cylindrical

Identifier

eqacylin

Graticule

Meridians: Equally spaced straight parallel lines.

Parallels: Unequally spaced straight parallel lines, perpendicular to the meridians. Spacing is closest near the poles.

Poles: Straight lines equal in length to the Equator.

Symmetry: About any meridian or the Equator.

Features


This is an orthographic projection onto a cylinder secant at the standard parallels. It is equal-area, but distortion of shape increases with distance from the standard parallels. Scale is true along the standard parallels and constant between two parallels equidistant from the Equator. This projection is not equidistant.

Parallels

For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, any latitude may be chosen; the default is arbitrarily set to 0° (the Lambert variation).

- This projection was proposed by Johann Heinrich Lambert (1772), a prolific cartographer who proposed seven different important projections. The form of this projection tangent at the Equator is often called the Lambert Equal-Area Cylindrical projection. That and other special forms of this projection are included separately in this guide, including the Gall Orthographic, the Behrmann Cylindrical, the Balthasart Cylindrical, and the Trystan Edwards Cylindrical projections.
- Mapping Toolbox uses a different implementation of the equal-area cylindrical projection for displaying coordinates on axesm-based maps than for projecting coordinates using the proj fwd or projinv function. These implementations may produce differing results.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('eqacylin', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History

eqdazim

Equidistant Azimuthal Projection

Classification

Azimuthal

Identifier

eqdazim

Graticule

The graticule described is for the polar aspect.

Meridians: Equally spaced straight lines intersecting at a central pole. The angles between them are the true angles.

Parallels: Equally spaced circles, centered on the central pole. The entire Earth may be shown.

Poles: Central pole is a point. The opposite pole is a bounding circle with a radius twice that of the Equator.

Symmetry: About any meridian.

Features

This is an equidistant projection. It is neither equal-area nor conformal. In the polar aspect, scale is true along any meridian. The projection is distortion free only at the center point. Distortion is moderate for the inner hemisphere, but it becomes extreme in the outer hemisphere.

Parallels

There are no standard parallels for azimuthal projections.


- This projection may have been first used by the ancient Egyptians for star charts. Several cartographers used it during the sixteenth century, including Guillaume Postel, who used it in 1581. Other names for this projection include Postel and Zenithal Equidistant.
- Mapping Toolbox uses a different implementation of the equidistant azimuthal projection for displaying coordinates on axesm-based maps than for projecting coordinates using the proj fwd or projiny function. These implementations may produce differing results.
- The implementation of the equidistant azimuthal projection for displaying coordinates on axesmbased maps is applicable only for coordinates that are referenced to a sphere. The implementation of the equidistant azimuthal projection for projecting coordinates using the projfwd or projinv function is applicable for coordinates referenced to either a sphere or an ellipsoid.

Limitations

This projection is available only on the sphere.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('eqdazim', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

eqdconic

Equidistant Conic Projection

Classification

Conic

Identifier

eqdconic

Graticule

Meridians: Equally spaced straight lines converging to a common point, usually beyond the pole. The angles between the meridians are less than the true angles.

Parallels: Equally spaced concentric circular arcs centered on the point of meridional convergence.

Poles: Normally circular arcs, enclosing the same angle as the displayed parallels.

Symmetry: About any meridian.

Features

Scale is true along each meridian and the one or two selected standard parallels. Scale is constant along any parallel. This projection is free of distortion along the two standard parallels. Distortion is constant along any other parallel. This projection provides a compromise in distortion between conformal and equal-area conic projections, of which it is neither.

Parallels

The cone of projection has interesting limiting forms. If a pole is selected as a single standard parallel, the cone is a plane, and an Equidistant Azimuthal projection results. If two parallels are chosen, not symmetric about the Equator, then an Equidistant Conic projection results. If a pole is selected as one of the standard parallels, then the projected pole is a point, otherwise the projected pole is an arc. If the Equator is so chosen, the cone becomes a cylinder and a Plate Carrée projection results. If two parallels equidistant from the Equator are chosen as the standard parallels, an Equidistant Cylindrical projection results. The default parallels are [15 75].

Remarks


In a rudimentary form, this projection dates back to Claudius Ptolemy, about A.D. 100. Improvements were developed by Johannes Ruysch in 1508, Gerardus Mercator in the late 16th century, and Nicolas de l'Isle in 1745. It is also known as the Simple Conic or Conic projection.

Limitations

Longitude data greater than 135° east or west of the central meridian is trimmed.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('eqdconic', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



See Also

eqdconicstd on page 11-52

Version History

egdconicstd

Equidistant Conic Projection — Standard

Identifier

egdconicstd

Graticule

Meridians: Equally spaced straight lines converging to a common point, usually beyond the pole. The angles between the meridians are less than the true angles.

Parallels: Equally spaced concentric circular arcs centered on the point of meridional convergence.

Poles: Normally circular arcs, enclosing the same angle as the displayed parallels.

Symmetry: About any meridian.

Features

egdconicstd implements the Equidistant Conic projection directly on a reference ellipsoid, consistent with the industry-standard definition of this projection. See egdconic on page 11-50 for an alternative implementation based on rotating the rectifying sphere.

Scale is true along each meridian and the one or two selected standard parallels. Scale is constant along any parallel. This projection is free of distortion along the two standard parallels. Distortion is constant along any other parallel. This projection provides a compromise in distortion between conformal and equal-area conic projections, of which it is neither.

Parallels

The cone of projection has interesting limiting forms. If a pole is selected as a single standard parallel, the cone is a plane, and an Equidistant Azimuthal projection results. If two parallels are chosen, not symmetric about the Equator, then an Equidistant Conic projection results. If a pole is selected as one of the standard parallels, then the projected pole is a point, otherwise the projected pole is an arc. If the Equator is so chosen, the cone becomes a cylinder and a Plate Carrée projection results. If two parallels equidistant from the Equator are chosen as the standard parallels, an Equidistant Cylindrical projection results. The default parallels are [15 75].


- In a rudimentary form, this projection dates back to Claudius Ptolemy, about A.D. 100. Improvements were developed by Johannes Ruysch in 1508, Gerardus Mercator in the late 16th century, and Nicolas de l'Isle in 1745. It is also known as the Simple Conic or Conic projection.
- Mapping Toolbox uses a different implementation of the standard equidistant conic projection for displaying coordinates on axesm-based maps than for projecting coordinates using the proj fwd or projiny function. These implementations may produce differing results.

Limitations

Longitude data greater than 135° east or west of the central meridian is trimmed.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('eqdconicstd', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



See Also

eqdconic on page 11-50

Version History

eqdcylin

Equidistant Cylindrical Projection

Classification

Cylindrical

Identifier

eqdcylin

Graticule

Meridians: Equally spaced straight parallel lines more than half as long as the Equator.

Parallels: Equally spaced straight parallel lines, perpendicular to and having wider spacing than the meridians.

Poles: Straight lines equal in length to the Equator.

Symmetry: About any meridian or the Equator.

Features

This is a projection onto a cylinder secant at the standard parallels. Distortion of both shape and area increase with distance from the standard parallels. Scale is true along all meridians (i.e., it is equidistant) and the standard parallels and is constant along any parallel and along the parallel of opposite sign.


Parallels

For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, any latitude can be chosen; the default is arbitrarily set to 30°.

- This projection was first used by Marinus of Tyre about A.D. 100. Special forms of this projection are the Plate Carrée, with a standard parallel at 0°, and the Gall Isographic, with standard parallels at 45°N and S. Other names for this projection include Equirectangular, Rectangular, Projection of Marinus, La Carte Parallélogrammatique, and Die Rechteckige Plattkarte.
- By default, the standard parallels are at +/- 30 degrees in geodetic latitude.
- When projecting a sphere, the origin vector is used to specify a triaxial rigid-body rotation.
- When projecting an ellipsoid:

- The origin longitude (2nd element of the origin vector) determines which meridian maps to the line x == false easting
- The origin latitude (1st element of the origin vector) is used to shift the natural origin off the equator via a constant *y*-offset, in addition to any false northing that may be specified.
- The grid convergence is fixed at 0, even if the 3rd element of the origin vector is nonzero.
- Mapping Toolbox uses a different implementation of the equidistant cylindrical projection for displaying coordinates on axesm-based maps than for projecting coordinates using the proj fwd or projinv function. These implementations may produce differing results.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('eqdcylin', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History

fournier

Fournier Projection

Classification

Pseudocylindrical

Identifier

fournier

Graticule

Meridians: Equally spaced elliptical curves converging at the poles.

Parallels: Straight lines.

Poles: Points.

Symmetry: About the Equator and central meridian.

Features

This projection is equal-area. Scale is constant along any parallel or pair of parallels equidistant from the Equator. This projection is neither equidistant nor conformal.


Parallels

There is no standard parallel for this projection.

Remarks

This projection was first described in 1643 by Georges Fournier. This is actually his second projection, the Fournier II.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('fournier', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

giso

Gall Isographic Projection

Classification

Cylindrical

Identifier

qiso

Graticule

Meridians: Equally spaced straight parallel lines more than half as long as the Equator.

Parallels: Equally spaced straight parallel lines, perpendicular to and having wider spacing than the meridians.

Poles: Straight lines equal in length to the Equator.

Symmetry: About any meridian or the Equator.

Features

This is a projection onto a cylinder secant at the 45° parallels. Distortion of both shape and area increase with distance from the standard parallels. Scale is true along all meridians (i.e., it is equidistant) and the two standard parallels, and is constant along any parallel and along the parallel of opposite sign.

Parallels


For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, the standard parallel is by definition fixed at **4**5º.

Remarks

- This projection is a specific case of the Equidistant Cylindrical projection, with standard parallels at 45°N and S.
- On the sphere, this projection can have an arbitrary, oblique aspect, as controlled by the Origin property of the axesm-based map. On the ellipsoid, only the equatorial aspect is supported.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('giso', 'Frame', 'on', 'Grid', 'on');
```

geoshow(landareas, 'FaceColor',[1 1 .5], 'EdgeColor',[.6 .6 .6]);
tissot;



Version History Introduced before R2006a

gortho

Gall Orthographic Projection

Classification

Cylindrical

Identifier

gortho

Graticule

Meridians: Equally spaced straight parallel lines.

Parallels: Unequally spaced straight parallel lines, perpendicular to the meridians. Spacing is closest near the poles.

Poles: Straight lines equal in length to the Equator.

Symmetry: About any meridian or the Equator.

Features

This is an orthographic projection onto a cylinder secant at the 45° parallels. It is equal-area, but distortion of shape increases with distance from the standard parallels. Scale is true along the standard parallels and constant between two parallels equidistant from the Equator. This projection is not equidistant.


Parallels

For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, the standard parallel is by definition fixed at **4**5º.

Remarks

This projection is named for James Gall, who originated it in 1855 and is a special form of the Equal-Area Cylindrical projection secant at 45°N and S. This projection is also known as the Peters projection.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('gortho', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

gstereo

Gall Stereographic Projection

Classification

Cylindrical

Identifier

astereo

Graticule

Meridians: Equally spaced straight parallel lines 0.77 as long as the Equator.

Parallels: Unequally spaced straight parallel lines, perpendicular to the meridians. Spacing increases toward the poles.

Poles: Straight lines equal in length to the Equator.

Symmetry: About any meridian or the Equator.

Features

This is a perspective projection from a point on the Equator opposite a given meridian onto a cylinder secant at the 45° parallels. It is not equal-area, equidistant, or conformal. Scale is true along the standard parallels and constant between two parallels equidistant from the Equator. There is no distortion along the standard parallels, but it increases moderately away from these parallels, becoming severe at the poles.

Parallels

For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, the standard parallel is by definition fixed at **4**5º.


Remarks

- This projection was presented by James Gall in 1855. It is also known simply as the Gall projection. It is a special form of the Braun Perspective Cylindrical projection secant at 45°N and
- This implementation of the Gall stereographic projection is applicable only for coordinates that are referenced to a sphere. If you want to project coordinates that are referenced to an ellipsoid, using the projfwd or projinv functions, then create a projers object instead of a map projection structure. You can create a projers object for the Gall stereographic projection using the ESRI authority code 54016. For example: projcrs (54016, 'Authority', 'ESRI').

 Mapping Toolbox uses a different implementation of the Gall stereographic projection for displaying coordinates on axesm-based maps than for projecting coordinates using the proj fwd or projinv function. These implementations may produce differing results.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('gstereo', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History

Introduced before R2006a

globe

Frame for 3-D map display on axesm-based map

Classification

Spherical

Identifier

alobe

Graticule

This map display is based on a coordinate transformation and is not a true map projection. Meridians, parallels, and displayed map data appear in a 3-D view that depends on the view and camera settings of the axesm-based map. Change the view interactively or by using the view function. Change the camera settings using the camposm, camtargm, and camupm functions.

Features

In the 3-D sense, globe is true in scale, equal-area, conformal, minimum error, and equidistant everywhere.

While globe has none of the distortions inherent in planar projections, it cannot be displayed without distortion or in its entirety. In order to render the globe in a figure window, either a perspective or orthographic transformation must be applied, both of which necessarily involve setting a viewpoint, hiding the back side and distortions of shape, scale, and angles.

Parallels

The globe requires no standard parallels.

Remarks

The globe display allows you to visualize terrain relief or other data for an entire planet viewed from space. Its underlying transformation maps latitude, longitude, and elevation to a 3-D Cartesian frame. The globe display is different from other transformations because it can render relative relief of elevations above, below, or on a sphere.

When displayed, the globe looks like an orthographic azimuthal projection, provided that the Projection property of the axesm-based map is set to 'orthographic'.


Display Geoid Heights on Globe

Display geoid heights from the EGM96 geoid model over a 3-D globe. First, get geoid heights and a geographic postings reference object. Load coastline latitude and longitude data.

```
[N,R] = egm96geoid;
load coastlines
```

Create a frame for the 3-D globe display using axesm. Set the line of sight for the globe using view. Turn off the axes background using axis off. Then, display the geoid heights and coastline data.

```
axesm('globe','Grid','on')
view(60,60)
axis off
meshm(N,R)
plotm(coastlat,coastlon)
```



Display Polygon on Globe

Display a polygon on a globe by converting the polygon to a data grid.

Create a sample polygon that contains a hole and rests on the surface of the globe. To do this, generate the vertices of its external and internal boundaries using the outlinegeoquad function. Specify the geographic limits as the first two arguments, and the vertex spacing in degrees as the

next two arguments. Reverse the order of the internal boundary vertices using the flip function, so they are in a counterclockwise order.

```
[latE,lonE] = outlinegeoquad([-35 35],[-30 30],0.25,0.25);
[latI,lonI] = outlinegeoquad([-15 15],[-15 15],0.25,0.25);
latI = flip(latI);
lonI = flip(lonI);
```

Combine the vertices into a single list by separating the boundaries with NaN values.

```
lat = [latE NaN latI]:
lon = [lonE NaN lonI];
```


The vectors lat and lon represent the boundaries of a polygon that contain a hole. Display the boundaries on the globe as a filled polygon by converting the polygon to a data grid.

To do this, create a geographic cells reference object for the globe and a grid of ones. Replace elements of the grid with the polygon data using the vec2mtx function. The new grid contains 0s to indicate the inside region of the polygon, 1s to indicate the boundaries, and 2s to indicate the outside region of the polygon.

```
R = georefcells([-90 90], [-180 180], 0.25, 0.25);
V = ones(R.RasterSize):
[V,R] = vec2mtx(lat,lon,V,R,'filled');
```


Create a globe using the axesm function. Display the data grid as an image using the geoshow function. Adjust the colormap so the inside region of the polygon is purple and the outside region is white. Change the camera line of sight using the view function, so the polygon is displayed on the near side of the globe.

```
axesm('globe','Grid','on')
geoshow(V,R,'DisplayType','texturemap')
colormap([0.5 0.5 0.8; 0 0 0; 1 1 1])
axis off
view(100,20)
```




The appearance of polygons on the globe is dependent on the camera line of sight and the globe transparency. For example, make the globe slightly transparent using the alpha function.

alpha(0.6)



When you view the polygon from the near side of the globe, the external boundary vertices appear in a clockwise order. When you view the polygon from the far side of the globe, the external boundary vertices appear in a counterclockwise order. When you rotate the globe so the polygon appears on both the near side and far side, then the polygon appears to intersect itself.



Version History Introduced before R2006a

See Also

geoshow|outlinegeoquad|axesm|vec2mtx

"Create and Display Polygons" on page 2-8

gnomonic

Gnomonic Projection

Classification

Azimuthal

Identifier

gnomonic

Graticule

The graticule described is for a polar aspect.

Meridians: Equally spaced straight lines intersecting at the central pole. The angles displayed are the true angles between meridians.

Parallels: Unequally spaced circles centered on the central pole. Spacing increases rapidly away from this pole. The Equator and the opposite hemisphere cannot be shown

Pole: The central pole is a point; the other pole is not shown.

Symmetry: About any meridian.

Features

This is a perspective projection from the center of the globe on a plane tangent at the center point, which is a pole in the common polar aspect, but can be any point. Less than one hemisphere can be shown with this projection, regardless of its center point. The significant property of this projection is that all great circles are straight lines. This is useful in navigation, as a great circle is the shortest path between two points on the globe. Only the center point enjoys true scale and zero distortion. This projection is neither conformal nor equal-area.

Parallels

There are no standard parallels for azimuthal projections.

Remarks

- This projection may have been first developed by Thales around 580 B.C. Its name is derived from the gnomon, the face of a sundial, since the meridians radiate like hour markings. This projection is also known as a gnomic or central projection.
- This implementation of the gnomonic projection is applicable only for coordinates that are referenced to a sphere.


 Mapping Toolbox uses a different implementation of the gnomonic projection for displaying coordinates on axesm-based maps than for projecting coordinates using the projfwd or projinv function. These implementations may produce differing results.

Limitations

Data greater than 65° distant from the center point is trimmed.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('gnomonic', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History

Introduced before R2006a

goode

Goode Homolosine Projection

Classification

Pseudocylindrical

Identifier

goode

Graticule

Central Meridian: Straight line 0.44 as long as the Equator.

Other Meridians: Equally spaced sinusoidal curves between the 40°44'11.8" parallels and elliptical arcs elsewhere, all concave toward the central meridian. The result is a slight, visible bend in the meridians at $40^{\circ}44'11.8''$ N and S.

Parallels: Straight parallel lines, perpendicular to the central meridian. Equally spaced between the 40°44'11.8" parallels, with gradually decreasing spacing outside these parallels.

Poles: Points.

Symmetry: About the central meridian or the Equator.

Features

This is an equal-area projection. Scale is true along all parallels and the central meridian between 40°44′11.8′′ N and S, and is constant along any parallel and between any pair of parallels equidistant from the Equator for all latitudes. Its distortion is identical to that of the Sinusoidal projection between 40°44'11.8" N and S, and to that of the Mollweide projection elsewhere. This projection is not conformal or equidistant.

Parallels

This projection has one standard parallel, which is by definition fixed at 0° .

Remarks


This projection was developed by J. Paul Goode in 1916. It is sometimes called simply the Homolosine projection, and it is usually used in an interrupted form. It is a merging of the Sinusoidal and Mollweide projections.

Limitations

This projection is available in an uninterrupted form only.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('goode', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History

Introduced before R2006a

hammer

Hammer Projection

Classification

Modified Azimuthal

Identifier

hammer

Graticule

Meridians: Central meridian is a straight line half the length of the Equator. Other meridians are complex curves, equally spaced along the Equator, and concave toward the central meridian.

Parallels: Equator is straight. Other parallels are complex curves, equally spaced along the central meridian, and concave toward the nearest pole.

Poles: Points.

Symmetry: About the Equator and central meridian.

Features

This projection is equal-area. The only point free of distortion is the center point. Distortion of shape is moderate throughout. This projection has less angular distortion on the outer meridians near the poles than pseudoazimuthal projections

Parallels


There is no standard parallel for this projection.

Remarks

- This projection was presented by H. H. Ernst von Hammer in 1892. It is a modification of the Lambert Azimuthal Equal Area projection. Inspired by Aitoff projection, it is also known as the Hammer-Aitoff. It in turn inspired the Briesemeister, a modified oblique Hammer projection. John Bartholomew's Nordic projection is an oblique Hammer centered on 45 degrees north and the Greenwich meridian. The Hammer projection is used in whole-world maps and astronomical maps in galactic coordinates.
- This implementation of the Hammer projection is applicable only for coordinates that are referenced to a sphere.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('hammer', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

hatano

Hatano Asymmetrical Equal-Area Projection

Classification

Pseudocylindrical

Identifier

hatano

Graticule

Central Meridian: Straight line 0.48 as long as the Equator.

Other Meridians: Equally spaced elliptical arcs concave toward the central meridian. The eccentricity of each ellipse changes at the Equator.

Parallels: Unequally spaced straight parallel lines, perpendicular to the central meridian. Spacing is not symmetrical about the Equator.

Poles: The North Pole is a line two-thirds the length of the Equator; the South Pole is a line threefourths the length of the Equator.

Symmetry: About the central meridian but *not* the Equator.

Features

This is an equal-area projection. Scale is true along 40°42'N and 38°27'S, and is constant along any parallel but generally not between pairs of parallels equidistant from the Equator. It is free of distortion only along the central meridian at $40^{\circ}42$ 'N and $38^{\circ}27$ 'S. This projection is not conformal or equidistant.

Parallels


Because of the asymmetrical nature of this projection, two standard parallels must be specified. The standard parallels are by definition fixed at 40°42'N and 38°27'S.

Remarks

This projection was presented by Masataka Hatano in 1972.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('hatano', 'Frame', 'on', 'Grid', 'on');
```

geoshow(landareas, 'FaceColor',[1 1 .5], 'EdgeColor',[.6 .6 .6]);
tissot;



Version History Introduced before R2006a

kavrsky5

Kavraisky V Projection

Classification

Pseudocylindrical

Identifier

kavrsky5

Graticule

Meridians: Complex curves converging at the poles. A sine function is used for y, but the meridians are not sine curves.

Parallels: Unequally spaced straight lines.

Poles: Points.

Symmetry: About the Equator and the central meridian.

Features

This is an equal-area projection. Scale is true along the fixed standard parallels at 35° , and 0.9 true along the Equator. This projection is neither conformal nor equidistant.


Parallels

The fixed standard parallels are at 35°.

Remarks

This projection was described by V. V. Kavraisky in 1933.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('kavrsky5', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

kavrsky6

Kavraisky VI Projection

Classification

Pseudocylindrical

Identifier

kavrsky6

Graticule

Central Meridian: Straight line half the length of the Equator.

Meridians: Sine curves (60º segments).

Parallels: Unequally spaced straight lines.

Poles: Straight lines half the length of the Equator.

Symmetry: About the Equator and the central meridian.

Features

This is an equal-area projection. Scale is constant along any parallel or pair of equidistant parallels. This projection is neither conformal nor equidistant.


Parallels

There are no standard parallels for this projection.

Remarks

This projection was described by V. V. Kavraisky in 1936. It is also called the Wagner I, for Karlheinz Wagner, who described it in 1932.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('kavrsky6', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

eqaazim

Lambert Azimuthal Equal-Area Projection

Classification

Azimuthal

Identifier

egaazim

Graticule

The graticule described is for a polar aspect.

Meridians: Equally spaced straight lines intersecting at the central pole. The angles displayed are the true angles between meridians.

Parallels: Unequally spaced circles centered on the central pole. The entire Earth can be shown. Spacing decreases away from the central pole.

Pole: The central pole is a point; the other pole is a bounding circle with 1.41 the radius of the Equator.

Symmetry: About any meridian.

Features

This nonperspective projection is equal-area. Only the center point is free of distortion, but distortion is moderate within 90° of this point. Scale is true only at the center point, increasing tangentially and decreasing radially with distance from the center point. This projection is neither conformal nor equidistant.


Parallels

There are no standard parallels for azimuthal projections.

Remarks

- This projection was presented by Johann Heinrich Lambert in 1772. It is also known as the Zenithal Equal-Area and the Zenithal Equivalent projection, and the Lorgna projection in its polar aspect.
- Mapping Toolbox uses a different implementation of the Lambert azimuthal equal-area projection for displaying coordinates on axesm-based maps than for projecting coordinates using the projfwd or projinv function. These implementations may produce differing results.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('eqaazim', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



lambert

Lambert Conformal Conic Projection

Classification

Conic

Identifier

lambert

Graticule

Meridians: Equally spaced straight lines converging at one of the poles. The angles between the meridians are less than the true angles.

Parallels: Unequally spaced concentric circular arcs centered on the pole of convergence. Spacing of parallels increases away from the central latitudes.

Poles: The pole nearest a standard parallel is a point, the other cannot be shown.

Symmetry: About any meridian.

Features

Scale is true along the one or two selected standard parallels. Scale is constant along any parallel and is the same in every direction at any point. This projection is free of distortion along the standard parallels. Distortion is constant along any other parallel. This projection is conformal everywhere but the poles; it is neither equal-area nor equidistant.

Parallels

The cone of projection has interesting limiting forms. If a pole is selected as a single standard parallel, the cone is a plane, and a Stereographic Azimuthal projection results. If two parallels are chosen, not symmetric about the Equator, then a Lambert Conformal Conic projection results. If a pole is selected as one of the standard parallels, then the projected pole is a point, otherwise the projected pole is an arc. If the Equator or two parallels equidistant from the Equator are chosen as the standard parallels, the cone becomes a cylinder, and a Mercator projection results. The default parallels are [15 75].

Remarks


This projection was presented by Johann Heinrich Lambert in 1772 and is also known as a Conical Orthomorphic projection.

Limitations

Longitude data greater than 135° east or west of the central meridian is trimmed. The default map limits are [0 90] to avoid extreme area distortion.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('lambert', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



See Also

lambertstd on page 11-86

lambertstd

Lambert Conformal Conic Projection — Standard

Classification

Conic

Identifier

lambertstd

Graticule

Meridians: Equally spaced straight lines converging at one of the poles. The angles between the meridians are less than the true angles.

Parallels: Unequally spaced concentric circular arcs centered on the pole of convergence. Spacing of parallels increases away from the central latitudes.

Poles: The pole nearest a standard parallel is a point, the other cannot be shown.

Symmetry: About any meridian.

Features

lambertstd implements the Lambert Conformal Conic projection directly on a reference ellipsoid, consistent with the industry-standard definition of this projection. See lambert on page 11-84 for an alternative implementation based on rotating the authalic sphere.

Scale is true along the one or two selected standard parallels. Scale is constant along any parallel and is the same in every direction at any point. This projection is free of distortion along the standard parallels. Distortion is constant along any other parallel. This projection is conformal everywhere but the poles; it is neither equal-area nor equidistant.

Parallels

The cone of projection has interesting limiting forms. If a pole is selected as a single standard parallel, the cone is a plane, and a Stereographic Azimuthal projection results. If two parallels are chosen, not symmetric about the Equator, then a Lambert Conformal Conic projection results. If a pole is selected as one of the standard parallels, then the projected pole is a point, otherwise the projected pole is an arc. If the Equator or two parallels equidistant from the Equator are chosen as the standard parallels, the cone becomes a cylinder, and a Mercator projection results. The default parallels are [15 75].

Remarks


- This projection was presented by Johann Heinrich Lambert in 1772 and is also known as a Conical Orthomorphic projection.
- Mapping Toolbox uses a different implementation of the standard Lambert conformal conic projection for displaying coordinates on axesm-based maps than for projecting coordinates using the projfwd or projinv function. These implementations may produce differing results.

Limitations

Longitude data greater than 135° east or west of the central meridian is trimmed. The default map limits are [0 90] to avoid extreme area distortion.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('lambertstd', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



See Also

lambert on page 11-84

Version History

Introduced before R2006a

lambcyln

Lambert Equal-Area Cylindrical Projection

Classification

Cylindrical

Identifier

lambcyln

Graticule

Meridians: Equally spaced straight parallel lines 0.32 as long as the Equator.

Parallels: Unequally spaced straight parallel lines, perpendicular to the meridians. Spacing is closest near the poles.

Poles: Straight lines equal in length to the Equator.

Symmetry: About any meridian or the Equator.

Features

This is an orthographic projection onto a cylinder tangent at the Equator. It is equal-area, but distortion of shape increases with distance from the Equator. Scale is true along the Equator and constant between two parallels equidistant from the Equator. This projection is not equidistant.


Parallels

For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, the standard parallel is by definition fixed at

Remarks

This projection is named for Johann Heinrich Lambert and is a special form of the Equal-Area Cylindrical projection tangent at the Equator.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('lambcyln', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

loximuth

Loximuthal Projection

Classification

Pseudocylindrical

Identifier

loximuth

Graticule

Central Meridian: Straight line at least half as long as the Equator. Actual length depends on the choice of central latitude. Length is 0.5 when the central latitude is the Equator, for example, and 0.65 for central latitudes of 40° .

Other Meridians: Complex curves intersecting at the poles and concave toward the central meridian.

Parallels: Equally spaced straight parallel lines, perpendicular to the central meridian.

Poles: Points.

Symmetry: About the central meridian. Symmetry about the Equator only when it is the central latitude.

Features

This projection has the special property that from the central point (the intersection of the central latitude with the central meridian), rhumb lines (loxodromes) are shown as straight, true to scale, and correct in azimuth from the center. This differs from the Mercator projection, in that rhumb lines are here shown in true scale and that unlike the Mercator, this projection does not maintain true azimuth for all points along the rhumb lines. Scale is true along the central meridian and is constant along any parallel, but not, generally, between parallels. It is free of distortion only at the central point and can be severely distorted in places. However, this projection is designed for its specific special property, in which distortion is not a concern.

Parallels


For this projection, only one standard parallel is specified: the central latitude described above. Specification of this central latitude defines the center of the loximuthal projection. The default value is 0º.

Remarks

This projection was presented by Karl Siemon in 1935 and independently by Waldo R. Tobler in 1966. The Bordone Oval projection of 1520 was very similar to the Equator-centered loximuthal. • This implementation of the loximuthal projection is applicable only for coordinates that are referenced to a sphere. If you want to project coordinates that are referenced to an ellipsoid, using the projfwd or projinv functions, then create a projcrs object instead of a map projection structure. You can create a projcrs object for the loximuthal projection using the ESRI authority code 54023. For example: projcrs (54023, 'Authority', 'ESRI').

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('loximuth', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

flatplrp

McBryde-Thomas Flat-Polar Parabolic Projection

Classification

Pseudocylindrical

Identifier

flatplrp

Graticule

Central Meridian: Straight line 0.48 as long as the Equator.

Other Meridians: Equally spaced parabolic curves concave toward the central meridian.

Parallels: Unequally spaced straight parallel lines, perpendicular to the central meridian. Spacing is greatest near the Equator.

Poles: Lines one-third as long as the Equator.

Symmetry: About the central meridian or the Equator.

Features

This is an equal-area projection. Scale is true along the $45^{\circ}30'$ parallels and is constant along any parallel and between any pair of parallels equidistant from the Equator. Distortion is severe near the outer meridians at high latitudes, but less so than on the pointed-polar projections. It is free of distortion only at the two points where the central meridian intersects the 45°30' parallels. This projection is not conformal or equidistant.


Parallels

For this projection, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. The standard parallel is by definition fixed at 45°30'.

Remarks

This projection was presented by F. Webster McBryde and Paul D. Thomas in 1949.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('flatplrp', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

flatplrq

McBryde-Thomas Flat-Polar Quartic Projection

Classification

Pseudocylindrical

Identifier

flatplrq

Graticule

Central Meridian: Straight line 0.45 as long as the Equator.

Other Meridians: Equally spaced quartic (fourth-order equation) curves concave toward the central meridian.

Parallels: Unequally spaced straight parallel lines, perpendicular to the central meridian. Spacing is greatest near the Equator.

Poles: Lines one-third as long as the Equator.

Symmetry: About the central meridian or the Equator.

Features

This is an equal-area projection. Scale is true along the 33°45' parallels and is constant along any parallel and between any pair of parallels equidistant from the Equator. Distortion is severe near the outer meridians at high latitudes, but less so than on the pointed-polar projections. It is free of distortion only at the two points where the central meridian intersects the 33°45' parallels. This projection is not conformal or equidistant.

Parallels


For this projection, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. The standard parallel is by definition fixed at $33^{\circ}45'$.

Remarks

This projection was presented by F. Webster McBryde and Paul D. Thomas in 1949, and is also known simply as the Flat-Polar Quartic projection.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('flatplrq', 'Frame', 'on', 'Grid', 'on');
```

geoshow(landareas, 'FaceColor',[1 1 .5], 'EdgeColor',[.6 .6 .6]);
tissot;



flatpirs

McBryde-Thomas Flat-Polar Sinusoidal Projection

Classification

Pseudocylindrical

Identifier

flatplrs

Graticule

Central Meridian: Straight line half as long as the Equator.

Other Meridians: Equally spaced sinusoidal curves intersecting at the poles and concave toward the central meridian.

Parallels: Unequally spaced straight parallel lines, perpendicular to the central meridian. Spacing is widest near the Equator.

Poles: Lines one-third as long as the Equator.

Symmetry: About the central meridian or the Equator.

Features

This projection is equal-area. Scale is true along the 55°51' parallels and is constant along any parallel and between any pair of parallels equidistant from the Equator. It is free of distortion only at the two points where the central meridian intersects the 55°51' parallels. This projection is not conformal or equidistant.


Parallels

For this projection, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. The standard parallel is by definition fixed at $55^{\circ}51'$.

Remarks

This projection was presented by F. Webster McBryde and Paul D. Thomas in 1949.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('flatplrs', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

mercator

Mercator Projection

Classification

Cylindrical

Identifier

mercator

Graticule

Meridians: Equally spaced straight parallel lines.

Parallels: Unequally spaced straight parallel lines, perpendicular to the meridians. Spacing increases toward the poles.

Poles: Cannot be shown.

Symmetry: About any meridian or the Equator.

Features

This is a projection with parallel spacing calculated to maintain conformality. It is not equal-area, equidistant, or perspective. Scale is true along the standard parallels and constant between two parallels equidistant from the Equator. It is also constant in all directions near any given point. Scale becomes infinite at the poles. The appearance of the Mercator projection is unaffected by the selection of standard parallels: they serve only to define the latitude of true scale.

The Mercator, which may be the most famous of all projections, has the special feature that all rhumb lines, or loxodromes (lines that make equal angles with all meridians, i.e., lines of constant heading), are straight lines. This makes it an excellent projection for navigational purposes. However, the extreme area distortion makes it unsuitable for general maps of large areas.

Parallels

For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, any latitude less than 86° may be chosen; the default is arbitrarily set to 0° .

Remarks

The Mercator projection is named for Gerardus Mercator, who presented it for navigation in 1569. It is now known to have been used for the Tunhuang star chart as early as 940 by Ch'ien Lo-Chih. It was first used in Europe by Erhard Etzlaub in 1511. It is also, but rarely, called the Wright projection, after Edward Wright, who developed the mathematics behind the projection in 1599.


 Mapping Toolbox uses a different implementation of the Mercator projection for displaying coordinates on axesm-based maps than for projecting coordinates using the projfwd or projinv function. These implementations may produce differing results.

Limitations

Data at latitudes greater than 86° is trimmed to prevent large y-values from dominating the display.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('mercator', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History

Introduced before R2006a

miller

Miller Cylindrical Projection

Classification

Cylindrical

Identifier

miller

Graticule

Meridians: Equally spaced straight parallel lines 0.73 as long as the Equator.

Parallels: Unequally spaced straight parallel lines, perpendicular to the meridians. Spacing increases toward the poles, less rapidly than that of the Mercator projection.

Poles: Straight lines equal in length to the Equator.

Symmetry: About any meridian or the Equator.

Features

This is a projection with parallel spacing calculated to maintain a look similar to the Mercator projection while reducing the distortion near the poles and allowing the poles to be displayed. It is not equal-area, equidistant, conformal, or perspective. Scale is true along the Equator and constant between two parallels equidistant from the Equator. There is no distortion near the Equator, and it increases moderately away from the Equator, but it becomes severe at the poles.

The Miller Cylindrical projection is derived from the Mercator projection; parallels are spaced from the Equator by calculating the distance on the Mercator for a parallel at 80% of the true latitude and dividing the result by 0.8. The result is that the two projections are almost identical near the Equator.

Parallels


For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, the standard parallel is by definition fixed at 0º.

Remarks

This projection was presented by Osborn Maitland Miller of the American Geographical Society in 1942. It is often used in place of the Mercator projection for atlas maps of the world, for which it is somewhat more appropriate.

- Mapping Toolbox uses a different implementation of the Miller projection for displaying coordinates on axesm-based maps than for projecting coordinates using the projfwd or projinv function. These implementations may produce differing results.
- The implementation of the Miller projection for displaying coordinates on axesm-based maps is applicable only for coordinates that are referenced to a sphere. The implementation of the Miller projection for projecting coordinates using the proj fwd or projinv function is applicable for coordinates referenced to either a sphere or an ellipsoid.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('miller', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



mollweid

Mollweide Projection

Classification

Pseudocylindrical

Identifier

mollweid

Graticule

Central Meridian: Straight line half as long as the Equator.

Other Meridians: Meridians 90° east and west of the central meridian form a circle. The others are equally spaced semiellipses intersecting at the poles and concave toward the central meridian.

Parallels: Unequally spaced straight parallel lines, perpendicular to the central meridian. Spacing is greatest toward the Equator, but the spacing changes gradually.

Poles: Points.

Symmetry: About the central meridian or the Equator.

Features

This is an equal-area projection. Scale is true along the $40^{\circ}44'$ parallels and is constant along any parallel and between any pair of parallels equidistant from the Equator. It is free of distortion only at the two points where the 40°44' parallels intersect the central meridian. This projection is not conformal or equidistant.

Parallels


For this projection, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. The standard parallel is by definition fixed at 40°44'.

Remarks

This projection was presented by Carl B. Mollweide in 1805. Its other names include the Homolographic, the Homalographic, the Babinet, and the Elliptical projections. It is occasionally used for thematic world maps, and it is combined with the Sinusoidal to produce the Goode Homolosine projection.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('mollweid', 'Frame', 'on', 'Grid', 'on');
```

geoshow(landareas, 'FaceColor',[1 1 .5], 'EdgeColor',[.6 .6 .6]);
tissot;



murdoch1

Murdoch I Conic Projection

Classification

Conic

Identifier

murdoch1

Graticule

Meridians: Equally spaced straight lines converging at one of the poles.

Parallels: Equally spaced concentric circular arcs.

Poles: Arcs, one of which might become a point in the limit.

Symmetry: About any meridian.

Features

This is an equidistant projection that is nearly minimum-error. Scale is true along any meridian and is constant along any parallel. Scale is also true along two standard parallels. These must be calculated, however (see remark on parallels below). The total area of the mapped area is correct, but it is not equal-area everywhere.

Parallels

The parallels for this projection are not standard parallels, but rather limiting parallels. The special feature of this map, correct total area, holds between these parallels. The default parallels are [15 75].


Remarks

- Described by Patrick Murdoch in 1758.
- This implementation of the Murdoch I conic projection is applicable only for coordinates that are referenced to a sphere.

Limitations

Longitude data greater than 135º east or west of the central meridian is trimmed.

```
landareas = shaperead('landareas.shp', 'UseGeoCoords',true);
axesm ('murdoch1', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor',[1 1 .5], 'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History

Introduced before R2006a

murdoch3

Murdoch III Minimum Error Conic Projection

Classification

Conic

Identifier

murdoch3

Graticule

Meridians: Equally spaced straight lines converging at one of the poles.

Parallels: Equally spaced concentric circular arcs.

Poles: Arcs, one of which might become a point in the limit.

Symmetry: About any meridian.

Features

This is an equidistant projection that is minimum-error. Scale is true along any meridian and is constant along any parallel. Scale is also true along two standard parallels. These must be calculated, however (see remark on parallels below). The total area of the mapped area is correct, but it is not equal-area everywhere.

Parallels

The parallels for this projection are not standard parallels, but rather limiting parallels. The special feature of this map, correct total area, holds between these parallels. The default parallels are [15 75].


Remarks

- Described by Patrick Murdoch in 1758, with errors corrected by Everett in 1904.
- This implementation of the Murdoch III minimum error conic projection is applicable only for coordinates that are referenced to a sphere.

Limitations

Longitude data greater than 135° east or west of the central meridian is trimmed.

landareas = shaperead('landareas.shp', 'UseGeoCoords',true);
axesm ('murdoch3', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor',[1 1 .5], 'EdgeColor',[.6 .6 .6]);
tissot;



Version History

Introduced before R2006a

ortho

Orthographic Projection

Classification

Azimuthal

Identifier

ortho

Graticule

The graticule described is for a polar aspect.

Meridians: Equally spaced straight lines intersecting at the central pole. The angles displayed are the true angles between meridians.

Parallels: Unequally spaced circles centered on the central pole. Spacing decreases away from this pole. The opposite hemisphere cannot be shown.

Pole: The central pole is a point; the other pole is not shown.

Symmetry: About any meridian.

Features

This is a perspective projection on a plane tangent at the center point from an infinite distance (that is, orthogonally). The center point is a pole in the common polar aspect, but can be any point. This projection has two significant properties. It looks like a globe, providing views of the Earth resembling those seen from outer space. Additionally, all great and small circles are either straight lines or elliptical arcs on this projection. Scale is true only at the center point and is constant in the circumferential direction along any circle having the center point as its center. Distortion increases rapidly away from the center point, the only place that is distortion-free. This projection is neither conformal nor equal-area.

Parallels

There are no standard parallels for azimuthal projections.

Remarks

- This projection appears to have been developed by the Egyptians and Greeks by the second century B.C.
- This implementation of the orthographic projection is applicable only for coordinates that are referenced to a sphere. If you want to project coordinates that are referenced to an ellipsoid,


- using the projfwd or projinv functions, then create a projcrs object instead of a map projection structure. You can create a projcrs object for the orthographic projection using the ESRI authority code 102037. For example: projcrs(102037, 'Authority', 'ESRI').
- Mapping Toolbox uses a different implementation of the orthographic projection for displaying coordinates on axesm-based maps than for projecting coordinates using the projfwd or projinv function. These implementations may produce differing results.

Limitations

Data greater than 89° distant from the center point is trimmed.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('ortho', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



pcarree

Plate Carree Projection

Classification

Cylindrical

Identifier

pcarree

Graticule

Meridians: Equally spaced straight parallel lines half as long as the Equator.

Parallels: Equally spaced straight parallel lines, perpendicular to and having the same spacing as the meridians.

Poles: Straight lines equal in length to the Equator.

Symmetry: About any meridian or the Equator.

Features

This is a projection onto a cylinder tangent at the Equator. Distortion of both shape and area increases with distance from the Equator. Scale is true along all meridians (i.e., it is equidistant) and the Equator and is constant along any parallel and along the parallel of opposite sign.


Parallels

For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, the standard parallel is by definition fixed at 0°.

Remarks

- This projection, like the more general Equidistant Cylindrical, is credited to Marinus of Tyre, thought to have invented it about A.D. 100. It may, in fact, have been originated by Erastosthenes, who lived approximately 275-195 B.C. The Plate Carrée has the most simply constructed graticule of any projection. It was used frequently in the 15th and 16th centuries and is quite common today in very simple computer mapping programs. It is the simplest and limiting form of the Equidistant Cylindrical projection. Another name for the Plate Carrée projection is the Simple Cylindrical. Its transverse aspect is the Cassini projection.
- On the sphere, this projection can have an arbitrary, oblique aspect, as controlled by the Origin property of the axesm-based map. On the ellipsoid, only the equatorial aspect is supported.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('pcarree', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History

Introduced before R2006a

polycon

Polyconic Projection

Classification

Polyconic

Identifier

polycon

Graticule

Central Meridian: A straight line.

Meridians: Complex curves spaced equally along the Equator and each parallel, and concave toward the central meridian.

Parallels: The Equator is a straight line. All other parallels are nonconcentric circular arcs spaced at true distances along the central meridian.

Poles: Normally circular arcs, enclosing the same angle as the displayed parallels.

Symmetry: About the Equator or the central meridian.

Features

For this projection, each parallel has a curvature identical to its curvature on a cone tangent at that latitude. Since each parallel has its own cone, this is a "polyconic" projection. Scale is true along the central meridian and along each parallel. This projection is free of distortion only along the central meridian; distortion can be severe at extreme longitudes. This projection is neither conformal nor equal-area.

Parallels

By definition, this projection has no standard parallels, since every parallel is a standard parallel.


Remarks

This projection was apparently originated about 1820 by Ferdinand Rudolph Hassler. It is also known as the American Polyconic and the Ordinary Polyconic projection.

Limitations

Longitude data greater than 75° east or west of the central meridian is trimmed.

landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('polycon', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;



See Also

polyconstd on page 11-114

Version History

Introduced before R2006a

polyconstd

Polyconic Projection — Standard

Classification

Polyconic

Identifier

polyconstd

Graticule

Central Meridian: A straight line.

Meridians: Complex curves spaced equally along the Equator and each parallel, and concave toward the central meridian.

Parallels: The Equator is a straight line. All other parallels are nonconcentric circular arcs spaced at true distances along the central meridian.

Poles: Normally circular arcs, enclosing the same angle as the displayed parallels.

Symmetry: About the Equator or the central meridian.

Features

polyconstd implements the Polyconic projection directly on a reference ellipsoid, consistent with the industry-standard definition of this projection. See polycon on page 11-112 for an alternative implementation based on rotating the rectifying sphere.

For this projection, each parallel has a curvature identical to its curvature on a cone tangent at that latitude. Since each parallel has its own cone, this is a "polyconic" projection. Scale is true along the central meridian and along each parallel. This projection is free of distortion only along the central meridian; distortion can be severe at extreme longitudes. This projection is neither conformal nor equal-area.

Parallels

By definition, this projection has no standard parallels, since every parallel is a standard parallel.

Remarks

This projection was apparently originated about 1820 by Ferdinand Rudolph Hassler. It is also known as the American Polyconic and the Ordinary Polyconic projection.


• Mapping Toolbox uses a different implementation of the standard polyconic projection for displaying coordinates on axesm-based maps than for projecting coordinates using the projfwd or projinv function. These implementations may produce differing results.

Limitations

Longitude data greater than 75° east or west of the central meridian is trimmed.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('polyconstd', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



See Also

polycon on page 11-112

Version History

Introduced before R2006a

putnins5

Putnins P5 Projection

Classification

Pseudocylindrical

Identifier

putnins5

Graticule

Central Meridian: Straight line half as long as the Equator.

Other Meridians: Equally spaced portions of hyperbolas intersecting at the poles and concave toward the central meridian.

Parallels: Equally spaced straight parallel lines, perpendicular to the central meridian.

Poles: Points.

Symmetry: About the central meridian or the Equator.

Features

Scale is true along the 21º14' parallels and is constant along any parallel, between any pair of parallels equidistant from the Equator, and along the central meridian. It is not free of distortion at any point. This projection is not equal-area, conformal, or equidistant.


Parallels

For this projection, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. The standard parallel is by definition fixed at 21º14'.

Remarks

- This projection was presented by Reinholds V. Putnins in 1934.
- This implementation of the Putnins P5 projection is applicable only for coordinates that are referenced to a sphere.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('putnins5', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

quartic

Quartic Authalic Projection

Classification

Pseudocylindrical

Identifier

quartic

Graticule

Central Meridian: Straight line 0.45 as long as the Equator.

Other Meridians: Equally spaced quartic (fourth-order equation) curves concave toward the central meridian.

Parallels: Unequally spaced straight parallel lines, perpendicular to the central meridian. Spacing changes gradually and is greatest near the Equator.

Poles: Points.

Symmetry: About the central meridian or the Equator.

Features

This is an equal-area projection. Scale is true along the Equator and is constant along any parallel and between any pair of parallels equidistant from the Equator. Distortion is severe near the outer meridians at high latitudes, but less so than on the Sinusoidal projection. It is free of distortion along the Equator. This projection is not conformal or equidistant.


Parallels

This projection has one standard parallel, which is by definition fixed at 0° .

Remarks

This projection was presented by Karl Siemon in 1937 and independently by Oscar Sherman Adams in 1945.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('quartic', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

robinson

Robinson Projection

Classification

Pseudocylindrical

Identifier

robinson

Graticule

Central Meridian: Straight line 0.51 as long as the Equator.

Other Meridians: Equally spaced, resemble elliptical arcs and are concave toward the central meridian.

Parallels: Straight parallel lines, perpendicular to the central meridian. Spacing is equal between the 38º parallels, decreasing outside these limits.

Poles: Lines 0.53 as long as the Equator.

Symmetry: About the central meridian or the Equator.

Features

Scale is true along the 38º parallels and is constant along any parallel or between any pair of parallels equidistant from the Equator. It is not free of distortion at any point, but distortion is very low within about 45° of the center and along the Equator. This projection is not equal-area, conformal, or equidistant; however, it is considered to look right for world maps, and hence is widely used by Rand McNally, the National Geographic Society, and others. This feature is achieved through the use of tabular coordinates rather than mathematical formulae for the graticules.

Parallels


For this projection, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. The standard parallel is by definition fixed at 38°.

Remarks

- This projection was presented by Arthur H. Robinson in 1963, and is also called the Orthophanic projection, which means right appearing.
- This implementation of the Robinson projection is applicable only for coordinates that are referenced to a sphere. If you want to project coordinates that are referenced to an ellipsoid, using the projfwd or projinv functions, then create a projcrs object instead of a map

- projection structure. You can create a projers object for the Robinson projection using the ESRI authority code 54030. For example: projers (54030, 'Authority', 'ESRI').
- Mapping Toolbox uses a different implementation of the Robinson projection for displaying coordinates on axesm-based maps than for projecting coordinates using the projfwd or projinv function. These implementations may produce differing results.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('robinson', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



sinusoid

Sinusoidal projection

Classification

Pseudocylindrical

Identifier

sinusoid

Graticule

Central Meridian: Straight line half as long as the Equator.

Other Meridians: Equally spaced sinusoidal curves intersecting at the poles and concave toward the central meridian.

Parallels: Equally spaced straight parallel lines, perpendicular to the central meridian.

Poles: Points.

Symmetry: About the central meridian or the Equator.

Features

This projection is equal-area. Scale is true along every parallel and along the central meridian. There is no distortion along the Equator or along the central meridian, but it becomes severe near the outer meridians at high latitudes.


Parallels

This projection has one standard parallel, which is by definition fixed at 0° .

Remarks

- This projection was developed in the 16th century. It was used by Jean Cossin in 1570 and by Jodocus Hondius in Mercator atlases of the early 17th century. It is the oldest pseudocylindrical projection currently in use, and is sometimes called the Sanson-Flamsteed or the Mercator Equal-Area projection.
- Mapping Toolbox uses a different implementation of the sinusoidal projection for displaying coordinates on axesm-based maps than for projecting coordinates using the projfwd or projinv function. These implementations may produce differing results.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('sinusoid', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



stereo

Stereographic Projection

Classification

Azimuthal

Identifier

stereo

Graticule

The graticule described is for a polar aspect.

Meridians: Equally spaced straight lines intersecting at the central pole. The angles displayed are the true angles between meridians.

Parallels: Unequally spaced circles centered on the central pole. Spacing increases gradually away from this pole.

Pole: The central pole is a point; the other pole is not shown.

Symmetry: About any meridian.

Features

This is a perspective projection on a plane tangent at the center point from the point antipodal to the center point. The center point is a pole in the common polar aspect, but can be any point. This projection has two significant properties. It is conformal, being free from angular distortion. Additionally, all great and small circles are either straight lines or circular arcs on this projection. Scale is true only at the center point and is constant along any circle having the center point as its center. This projection is not equal-area.

Parallels

There are no standard parallels for azimuthal projections.

Remarks


- The polar aspect of this projection appears to have been developed by the Egyptians and Greeks by the second century B.C.
- Mapping Toolbox uses a different implementation of the stereographic projection for displaying coordinates on axesm-based maps than for projecting coordinates using the projfwd or projinv function. These implementations may produce differing results.

Limitations

Data greater than $90^{\mbox{\tiny o}}$ distant from the center point is trimmed.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('stereo', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



modsine

Tissot Modified Sinusoidal Projection

Classification

Pseudocylindrical

Identifier

modsine

Graticule

Meridians: Sine curves converging at the Poles.

Parallels: Equally spaced straight lines.

Poles: Points.

Symmetry: About the Equator and the central meridian

Features

This is an equal-area projection. Scale is constant along any parallel or any pair of equidistant parallels, and along the central meridian. It is not equidistant or conformal.

Parallels

There are no standard parallels for this projection.


Remarks

This projection was first described by N. A. Tissot in 1881

Limitations

This projection is available only for the sphere.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('modsine', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

tranmerc

Transverse Mercator Projection

Classification

Cylindrical

Identifier

tranmerc

Features


This conformal projection is the transverse form of the Mercator projection and is also known as the Gauss-Krueger projection. It is not equal area, equidistant, or perspective.

The scale is constant along the central meridian, and increases to the east and west. The scale at the central meridian can be set true to scale, or reduced slightly to render the mean scale of the overall map more correctly.

Remarks

- The uniformity of scale along its central meridian makes transverse Mercator an excellent choice for mapping areas that are elongated north-to-south. Its best known application is the definition of Universal Transverse Mercator (UTM) coordinates. Each UTM zone spans only 6 degrees of longitude, but the northern half extends from the equator all the way to 84 degrees north and the southern half extends from 80 degrees south to the equator. Other map grids based on transverse Mercator include many of the state plane zones in the U.S. and the U.K. National Grid.
- Mapping Toolbox uses a different implementation of the transverse Mercator projection for displaying coordinates on axesm-based maps than for projecting coordinates using the proj fwd or projiny function. These implementations may produce differing results.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('tranmerc', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

trystan

Trystan Edwards Cylindrical Projection

Classification

Cylindrical

Identifier

trystan

Graticule

Meridians: Equally spaced straight parallel lines.

Parallels: Unequally spaced straight parallel lines, perpendicular to the meridians. Spacing is closest near the poles.

Poles: Straight lines equal in length to the Equator.

Symmetry: About any meridian or the Equator.

Features

This is an orthographic projection onto a cylinder secant at the 37°24' parallels. It is equal-area, but distortion of shape increases with distance from the standard parallels. Scale is true along the standard parallels and constant between two parallels equidistant from the Equator. This projection is not equidistant.


Parallels

For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, the standard parallel is by definition fixed at 37º24'.

Remarks

This projection is named for Trystan Edwards, who presented it in 1953. It is a special form of the Equal-Area Cylindrical projection secant at 37°24'N and S.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('trystan', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



ups

Universal Polar Stereographic System

Classification

Azimuthal

Identifier

ups

Graticule

The graticule described is for the southern zone.

Meridians: Equally spaced straight lines centered on the South Pole. The angles displayed are the true angles between meridians.

Parallels: Unequally spaced circles centered on the South Pole. Spacing increases gradually away from the circle of true scale along latitude 87 degrees, 7 minutes N. The opposite pole cannot be shown.

Poles: The South Pole is a point. The North Pole is not shown.

Symmetry: About any meridian.

Features

This is a perspective projection on a plane tangent to either the North or South Pole. It is conformal, being free from angular distortion. Additionally, all great and small circles are either straight lines or circular arcs on this projection. Scale is true along latitudes 87 degrees, 7 minutes N or S, and is constant along any other parallel. This projection is not equal area.

Parallels

The parallels 87 degrees, 7 minutes N and S are lines of true scale by virtue of the scale factor. There are no standard parallels for azimuthal projections.

Remarks

This projection is a special case of the stereographic projection in the polar aspect. It is used as part of the Universal Transverse Mercator (UTM) system to extend coverage to the poles. This projection has two zones: "North" for latitudes 84° N to 90° N, and "South" for latitudes 80° S to 90° S. The defaults for this projection are: scale factor is 0.994, false easting and northing are 2,000,000 meters. The international ellipsoid in units of meters is used as the geoid model.

• Mapping Toolbox uses a different implementation of the UPS projection for displaying coordinates on axesm-based maps than for projecting coordinates using the projfwd or projinv function. These implementations may produce differing results.

Version History

Introduced in R2006a

utm

Universal Transverse Mercator System

Classification

Cvlindrical

Identifier

utm

Graticule

Meridians: Complex curves concave toward the central meridian.

Parallels: Complex curves concave toward the nearest pole.

Poles: Not shown.

Symmetry: About the central meridian or the Equator.

Features

This is a conformal projection with parameters chosen to minimize distortion over a defined set of small areas. It is not equal area, equidistant, or perspective. Scale is true along two straight lines on the map approximately 180 kilometers east and west of the central meridian, and is constant along other straight lines equidistant from the central meridian. Scale is less than true between, and greater than true outside the lines of true scale.

Parallels

There are no standard parallels for this projection. There are two lines of zero distortion by virtue of the scale factor.

Remarks

The UTM system divides the world between 80° S and 84° degrees N into a set of quadrangles called zones. Zones generally cover 6 degrees of longitude and 8 degrees of latitude. Each zone has a set of defined projection parameters, including central meridian, false eastings and northings and the reference ellipsoid. The projection equations are the Gauss-Krüger versions of the Transverse Mercator. The projected coordinates form a grid system, in which a location is specified by the zone, easting and northing.

The UTM system was introduced in the 1940s by the U.S. Army. It is widely used in topographic and military mapping.

Version History Introduced in R2006a

vgrint1

Van der Grinten I Projection

Classification

Polyconic

Identifier

vgrint1

Graticule

Central Meridian: A straight line.

Meridians: Circular curves spaced equally along the equator and concave toward the central meridian.

Parallels: The Equator is a straight line. All other parallels are circular arcs concave toward the nearest pole.

Poles: Points.

Symmetry: About the Equator or the central meridian.

Features

In this projection, the world is enclosed in a circle. Scale is true along the Equator and increases rapidly away from the Equator. Area distortion is extreme near the poles. This projection is neither conformal nor equal-area.

Parallels

There are no standard parallels for this projection.


- This projection was presented by Alphons J. Van der Grinten in 1898. He obtained a U.S. patent for it in 1904. It is also known simply as the Van der Grinten projection (without the "I").
- Mapping Toolbox uses a different implementation of the Van der Grinten I projection for displaying coordinates on axesm-based maps than for projecting coordinates using the projfwd or projinv function. These implementations may produce differing results.
- The implementation of the Van der Grinten I projection for displaying coordinates on axesm-based maps is applicable only for coordinates that are referenced to a sphere. The implementation of the Van der Grinten I projection for projecting coordinates using the projfwd or projinv function is applicable for coordinates referenced to either a sphere or an ellipsoid.

Limitations

This projection is available only for the sphere.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('vgrintl', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



vperspec

Vertical Perspective Azimuthal Projection

Classification

Azimuthal

Identifier

vperspec

Graticule

The graticule described is for a polar aspect.

Meridians: Equally spaced straight lines intersecting at the central pole. The angles displayed are true angles between meridians.

Parallels: Unequally spaced circles centered on the central pole. Spacing decreases away from this pole. The opposite hemisphere cannot be shown, nor can distant parts of the closer hemisphere. The limit of visibility depends on the observation altitude.

Poles: The central pole is a point. The other pole is not shown.

Symmetry: About any meridian.

Features

This is a perspective projection on a plane tangent at the center point from a finite distance. Scale is true only at the center point, and is constant in the circumferential direction along any circle having the center point as its center. Distortion increases rapidly away from the center point, the only point which is distortion free. This projection is neither conformal nor equal area.


- This projection provides views of the globe resembling those seen from a spacecraft in orbit. The Orthographic projection is a limiting form with the observer at an infinite distance.
- This projection requires a view altitude parameter, which specifies the observer's altitude above the origin point. Because this parameter is unique to this projection and because the projection does not need any standard parallels, a special workaround is used. Rather than add an extra axesm-based map property just for vperspec, the MapParallels property is repurposed instead. You should assign the desired view altitude value to the MapParallels property. Provide a scalar value for length in the same units as the earth radius or semi-major axis length used in the axesm-based map reference ellipsoid ('Geoid') property.
- This implementation of the vertical perspective azimuthal projection is applicable only for coordinates that are referenced to a sphere.

Limitations

Data more distant than the limit of visibility is trimmed.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('vperspec', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



wagner4

Wagner IV Projection

Classification

Pseudocylindrical

Identifier

wagner4

Graticule

Central Meridian: Straight line half as long as the Equator.

Other Meridians: Equally spaced portions of ellipses concave toward the central meridian. The meridians 103°55' east and west of the central meridian are circular arcs.

Parallels: Unequally spaced straight parallel lines, perpendicular to the central meridian. Spacing is greatest toward the Equator.

Poles: Lines half as long as the Equator.

Symmetry: About the central meridian or the Equator.

Features

This is an equal-area projection. Scale is true along the $42^{\circ}59'$ parallels and is constant along any parallel and between any pair of parallels equidistant from the Equator. Distortion is not as extreme near the outer meridians at high latitudes as for pointed-polar pseudocylindrical projections, but there is considerable distortion throughout the polar regions. It is free of distortion only at the two points where the 42°59' parallels intersect the central meridian. This projection is not conformal or equidistant.

Parallels


For this projection, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. The standard parallel is by definition fixed at $42^{\circ}59$ '.

Remarks

This projection was presented by Karlheinz Wagner in 1932.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('wagner4', 'Frame', 'on', 'Grid', 'on');
```

geoshow(landareas, 'FaceColor',[1 1 .5], 'EdgeColor',[.6 .6 .6]);
tissot;



werner

Werner Projection

Classification

Pseudoconic

Identifier

werner

Graticule

Central Meridian: A straight line.

Meridians: Complex curves connecting points equally spaced along each parallel and concave toward the central meridian.

Parallels: Concentric circular arcs spaced at true distances along the central meridian, centered on one of the poles.

Poles: Points.

Symmetry: About the central meridian.

Features

This is an equal-area projection. It is a Bonne projection with one of the poles as its standard parallel. The central meridian is free of distortion. This projection is not conformal. Its heart shape gives it the additional descriptor cordiform.


Parallels

The standard parallel for this projection is set to 90° N.

Remarks

This projection was developed by Johannes Stabius (Stab) about 1500 and was promoted by Johannes Werner in 1514. It is also called the Stab-Werner projection.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('werner', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas, 'FaceColor', [1 1 .5], 'EdgeColor', [.6 .6 .6]);
tissot;
```



Version History Introduced before R2006a

wetch

Wetch Cylindrical Projection

Classification

Cylindrical

Identifier

wetch

Graticule

Central Meridian: Straight line (includes meridian opposite the central meridian in one continuous line).

Other Meridians: Straight lines if 90° from central meridian, complex curves concave toward the central meridian otherwise.

Parallels: Complex curves concave toward the nearest pole.

Poles: Points along the central meridian.

Symmetry: About any straight meridian or the Equator.

Features

This is a perspective projection from the center of the Earth onto a cylinder tangent to the central meridian. It is not equal-area, equidistant, or conformal. Scale is true along the central meridian and constant between two points equidistant in x and y from the central meridian. There is no distortion along the central meridian, but it increases rapidly away from the central meridian in the y-direction.

Parallels

For cylindrical projections, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. For this projection, which is the transverse aspect of the Central Cylindrical, the standard parallel of the base projection is by definition fixed at 0°.


- This is the transverse aspect of the Central Cylindrical projection discussed by J. Wetch in the early 19th century.
- This implementation of the Wetch cylindrical projection is applicable only for coordinates that are referenced to a sphere.

Limitations

To prevent large y-values from dominating the display, data at y-values that would correspond to latitudes of greater than 75° in the normal aspect of the Central Cylindrical projection is trimmed.

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('wetch', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



wiechel

Wiechel Projection

Classification

Pseudoazimuthal

Identifier

wiechel

Graticule

The graticule described is for a polar aspect.

Meridians: Equally spaced semicircles from pole to pole, concave toward the west.

Parallels: Concentric circles.

Pole: The central pole is a point; the other pole is a bounding circle.

Symmetry: Radially about the center point.

Features

This equal-area projection is a novelty map, usually centered at a pole, showing semicircular meridians in a pinwheel arrangement. Scale is correct along the meridians. This projection is not conformal.

Parallels

There are no standard parallels for azimuthal projections.

Remarks


- This projection was presented by H. Wiechel in 1879.
- This implementation of the Wiechel projection is applicable only for coordinates that are referenced to a sphere.

Limitations

Data greater than 65° distant from the center point is trimmed.

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('wiechel', 'Frame', 'on', 'Grid', 'on');
```

geoshow(landareas, 'FaceColor',[1 1 .5], 'EdgeColor',[.6 .6 .6]);
tissot;



Version History Introduced before R2006a

winkel

Winkel I Projection

Classification

Pseudocylindrical

Identifier

winkel

Graticule

Central Meridian: Straight line at least half as long as the Equator.

Other Meridians: Equally spaced sinusoidal curves concave toward the central meridian.

Parallels: Equally spaced straight parallel lines, perpendicular to the central meridian.

Poles: Lines at least half as long as the Equator.

Symmetry: About the central meridian or the Equator.

Features

This projection is an arithmetical average of the x and y coordinates of the Sinusoidal and Equidistant Cylindrical projections. Scale is true along the standard parallels and is constant along any parallel and between any pair of parallels equidistant from the Equator. There is no point free of distortion. This projection is not equal-area, conformal, or equidistant.


Parallels

For this projection, only one standard parallel is specified. The other standard parallel is the same latitude with the opposite sign. Any latitude may be chosen; the default is set to $50^{\circ}28'$.

- This projection was developed by Oswald Winkel in 1914. Its limiting form is the Eckert V when a standard parallel of 0° is chosen.
- This implementation of the Winkel I projection is applicable only for coordinates that are referenced to a sphere. If you want to project coordinates that are referenced to an ellipsoid, using the projfwd or projinv functions, then create a projers object instead of a map projection structure. You can create a projers object for the Winkel I projection using the ESRI authority code 54018. For example: projcrs (54018, 'Authority', 'ESRI').

Example

```
landareas = shaperead('landareas.shp','UseGeoCoords',true);
axesm ('winkel', 'Frame', 'on', 'Grid', 'on');
geoshow(landareas,'FaceColor',[1 1 .5],'EdgeColor',[.6 .6 .6]);
tissot;
```



Version History

Introduced before R2006a