NAG Fortran Library Routine Document

D03PSF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

D03PSF integrates a system of linear or nonlinear convection-diffusion equations in one space dimension, with optional source terms and scope for coupled ordinary differential equations (ODEs). The system must be posed in conservative form. This routine also includes the option of automatic adaptive spatial remeshing. Convection terms are discretised using a sophisticated upwind scheme involving a user-supplied numerical flux function based on the solution of a Riemann problem at each mesh point. The method of lines is employed to reduce the partial differential equations (PDEs) to a system of ODEs, and the resulting system is solved using a backward differentiation formula (BDF) method or a Theta method.

2 Specification

SUBROUTINE DO3PS	F(NPDE, TS, TOUT, PDEDEF, NUMFLX, BNDARY, UVINIT, U,
1	NPTS, X, NCODE, ODEDEF, NXI, XI, NEQN, RTOL, ATOL,
2	ITOL, NORM, LAOPT, ALGOPT, REMESH, NXFIX, XFIX,
3	NRMESH, DXMESH, TRMESH, IPMINF, XRATIO, CONST, MONITF,
4	W, NW, IW, NIW, ITASK, ITRACE, IND, IFAIL)
INTEGER	NPDE, NPTS, NCODE, NXI, NEQN, ITOL, NXFIX, NRMESH,
1	IPMINF, NW, IW(NIW), NIW, ITASK, ITRACE, IND, IFAIL
<i>real</i>	TS, TOUT, U(NEQN), X(NPTS), XI(*), RTOL(*), ATOL(*),
1	ALGOPT(30), XFIX(*), DXMESH, TRMESH, XRATIO, CONST,
2	W(NW)
LOGICAL	REMESH
CHARACTER*1	NORM, LAOPT
EXTERNAL	PDEDEF, NUMFLX, BNDARY, UVINIT, ODEDEF, MONITF

3 Description

D03PSF integrates the system of convection-diffusion equations in conservative form:

$$\sum_{j=1}^{\text{NPDE}} P_{i,j} \frac{\partial U_j}{\partial t} + \frac{\partial F_i}{\partial x} = C_i \frac{\partial D_i}{\partial x} + S_i, \tag{1}$$

or the hyperbolic convection-only system:

$$\frac{\partial U_i}{\partial t} + \frac{\partial F_i}{\partial x} = 0, \tag{2}$$

for i = 1, 2, ..., NPDE, $a \le x \le b, t \ge t_0$, where the vector U is the set of PDE solution values

$$U(x,t) = [U_1(x,t), \dots, U_{\text{NPDE}}(x,t)]^T.$$

The optional coupled ODEs are of the general form

$$R_i(t, V, \dot{V}, \xi, U^*, U^*_x, U^*_t) = 0, \quad i = 1, 2, \dots, \text{NCODE},$$
(3)

where the vector V is the set of ODE solution values

$$V(t) = [V_1(t), \dots, V_{\text{NCODE}}(t)]^T$$

 \dot{V} denotes its derivative with respect to time, and U_x is the spatial derivative of U.

In (2), $P_{i,j}$, F_i and C_i depend on x, t, U and V; D_i depends on x, t, U, U_x and V; and S_i depends on x, t, U, V and **linearly** on \dot{V} . Note that $P_{i,j}$, F_i , C_i and S_i must not depend on any space derivatives, and $P_{i,j}$,

 F_i , C_i and D_i must not depend on any time derivatives. In terms of conservation laws, F_i , $C_i \partial D_i / \partial x$ and S_i are the convective flux, diffusion and source terms respectively.

In (3), ξ represents a vector of n_{ξ} spatial coupling points at which the ODEs are coupled to the PDEs. These points may or may not be equal to PDE spatial mesh points. U^* , U^*_x and U^*_t are the functions U, U_x and U_t evaluated at these coupling points. Each R_i may depend only linearly on time derivatives. Hence (3) may be written more precisely as

$$R = L - M\dot{V} - NU_t^*,\tag{4}$$

where $\mathbf{R} = [R_1, \dots, R_{\text{NCODE}}]^T$, *L* is a vector of length NCODE, *M* is an NCODE by NCODE matrix, *N* is an NCODE by $(n_{\xi} \times \text{NPDE})$ matrix and the entries in *L*, *M* and *N* may depend on *t*, ξ , U^* , U_x^* and *V*. In practice the user only needs to supply a vector of information to define the ODEs and not the matrices *L*, *M* and *N*. (See Section 5 for the specification of the user-supplied procedure ODEDEF.)

The integration in time is from t_0 to t_{out} , over the space interval $a \le x \le b$, where $a = x_1$ and $b = x_{NPTS}$ are the leftmost and rightmost points of a user-defined mesh $x_1, x_2, \ldots, x_{NPTS}$ defined initially by the user and (possibly) adapted automatically during the integration according to user-specified criteria.

The initial $(t = t_0)$ values of the functions U(x, t) and V(t) must be specified in a subroutine UVINIT supplied by the user. Note that UVINIT will be called again following any initial remeshing, and so $U(x, t_0)$ should be specified for **all** values of x in the interval $a \le x \le b$, and not just the initial mesh points.

The PDEs are approximated by a system of ODEs in time for the values of U_i at mesh points using a spatial discretisation method similar to the central-difference scheme used in D03PCF/D03PCA, D03PHF/D03PHA and D03PPF/D03PPA, but with the flux F_i replaced by a *numerical flux*, which is a representation of the flux taking into account the direction of the flow of information at that point (i.e., the direction of the characteristics). Simple central differencing of the numerical flux then becomes a sophisticated upwind scheme in which the correct direction of upwinding is automatically achieved.

The numerical flux, \hat{F}_i say, must be calculated by the user in terms of the *left* and *right* values of the solution vector U (denoted by U_L and U_R respectively), at each mid-point of the mesh $x_{j-\frac{1}{2}} = (x_{j-1} + x_j)/2$ for $j = 2, 3, \ldots$, NPTS. The left and right values are calculated by D03PSF from two adjacent mesh points using a standard upwind technique combined with a Van Leer slope-limiter (see LeVeque (1990)). The physically correct value for \hat{F}_i is derived from the solution of the Riemann problem given by

$$\frac{\partial U_i}{\partial t} + \frac{\partial F_i}{\partial y} = 0,\tag{5}$$

where $y = x - x_{j-\frac{1}{2}}$, i.e., y = 0 corresponds to $x = x_{j-\frac{1}{2}}$, with discontinuous initial values $U = U_L$ for y < 0 and $U = U_R$ for y > 0, using an *approximate Riemann solver*. This applies for either of the systems (1) or (2); the numerical flux is independent of the functions $P_{i,j}$, C_i , D_i and S_i . A description of several approximate Riemann solvers can be found in LeVeque (1990) and Berzins *et al.* (1989). Roe's scheme (Roe (1981)) is perhaps the easiest to understand and use, and a brief summary follows. Consider the system of PDEs $U_t + F_x = 0$ or equivalently $U_t + AU_x = 0$. Provided the system is linear in U, i.e., the Jacobian matrix A does not depend on U, the numerical flux \hat{F} is given by

$$\hat{F} = \frac{1}{2}(F_L + F_R) - \frac{1}{2}\sum_{k=1}^{\text{NPDE}} \alpha_k |\lambda_k| e_k,$$
(6)

where F_L (F_R) is the flux F calculated at the left (right) value of U, denoted by U_L (U_R); the λ_k are the eigenvalues of A; the e_k are the right eigenvectors of A; and the α_k are defined by

$$U_R - U_L = \sum_{k=1}^{\text{NPDE}} \alpha_k e_k.$$
(7)

Examples are given in the documents for D03PFF and D03PLF.

If the system is nonlinear, Roe's scheme requires that a linearized Jacobian is found (see Roe (1981)).

The functions $P_{i,j}$, C_i , D_i and S_i (but **not** F_i) must be specified in a subroutine PDEDEF supplied by the user. The numerical flux \hat{F}_i must be supplied in a separate user-supplied subroutine NUMFLX. For problems in the form (2), the actual argument D03PLP may be used for PDEDEF (D03PLP is included in the NAG Fortran Library; however, its name may be implementation-dependent: see the Users' Note for your implementation for details). D03PLP sets the matrix with entries $P_{i,j}$ to the identity matrix, and the functions C_i , D_i and S_i to zero.

For second-order problems i.e., diffusion terms present, a boundary condition is required for each PDE at both boundaries for the problem to be well-posed. If there are no diffusion terms present, then the continuous PDE problem generally requires exactly one boundary conditions for each PDE, that is NPDE boundary conditions in total. However, in common with most discretisation schemes for first-order problems, a *numerical boundary condition* is required at the other boundary for each PDE. In order to be consistent with the characteristic directions of the PDE system, the numerical boundary conditions must be derived from the solution inside the domain in some manner (see below). Both types of boundary conditions must be supplied by the user, i.e., a total of NPDE conditions at each boundary point.

The position of each boundary condition should be chosen with care. In simple terms, if information is flowing into the domain then a physical boundary condition is required at that boundary, and a numerical boundary condition is required at the other boundary. In many cases the boundary conditions are simple, e.g., for the linear advection equation. In general the user should calculate the characteristics of the PDE system and specify a physical boundary condition for each of the characteristic variables associated with incoming characteristics, and a numerical boundary condition for each outgoing characteristic.

A common way of providing numerical boundary conditions is to extrapolate the characteristic variables from the inside of the domain (note that when using banded matrix algebra the fixed bandwidth means that only linear extrapolation is allowed, i.e., using information at just two interior points adjacent to the boundary). For problems in which the solution is known to be uniform (in space) towards a boundary during the period of integration then extrapolation is unnecessary; the numerical boundary condition can be supplied as the known solution at the boundary. Another method of supplying numerical boundary conditions involves the solution of the characteristic equations associated with the outgoing characteristics. Examples of both methods can be found in the documents for D03PFF and D03PLF.

The boundary conditions must be specified in a subroutine BNDARY (provided by the user) in the form

$$G_i^L(x, t, U, V, \dot{V}) = 0$$
 at $x = a, \quad i = 1, 2, \dots, \text{NPDE},$ (8)

at the left-hand boundary, and

$$G_i^{\mathbb{R}}(x, t, U, V, \dot{V}) = 0 \quad \text{at} \quad x = b, \quad i = 1, 2, \dots, \text{NPDE},$$
(9)

at the right-hand boundary.

Note that spatial derivatives at the boundary are not passed explicitly to the subroutine BNDARY, but they can be calculated using values of U at and adjacent to the boundaries if required. However, it should be noted that instabilities may occur if such one-sided differencing opposes the characteristic direction at the boundary.

The algebraic-differential equation system which is defined by the functions R_i must be specified in a subroutine ODEDEF supplied by the user. The user must also specify the coupling points ξ (if any) in the array XI.

In total there are NPDE \times NPTS + NCODE ODEs in the time direction. This system is then integrated forwards in time using a BDF or Theta method, optionally switching between Newton's method and functional iteration (see Berzins *et al.* (1989) and the references therein).

The adaptive space remeshing can be used to generate meshes that automatically follow the changing timedependent nature of the solution, generally resulting in a more efficient and accurate solution using fewer mesh points than may be necessary with a fixed uniform or non-uniform mesh. Problems with travelling wavefronts or variable-width boundary layers for example will benefit from using a moving adaptive mesh. The discrete time-step method used here (developed by Furzeland (1984)) automatically creates a new mesh based on the current solution profile at certain time-steps, and the solution is then interpolated onto the new mesh and the integration continues. The method requires the user to supply a subroutine MONITF which specifies in an analytical or numerical form the particular aspect of the solution behaviour the user wishes to track. This so-called monitor function is used by the routines to choose a mesh which equally distributes the integral of the monitor function over the domain. A typical choice of monitor function is the second space derivative of the solution value at each point (or some combination of the second space derivatives if there is more than one solution component), which results in refinement in regions where the solution gradient is changing most rapidly.

The user specifies the frequency of mesh updates together with certain other criteria such as adjacent mesh ratios. Remeshing can be expensive and the user is encouraged to experiment with the different options in order to achieve an efficient solution which adequately tracks the desired features of the solution.

Note that unless the monitor function for the initial solution values is zero at all user-specified initial mesh points, a new initial mesh is calculated and adopted according to the user-specified remeshing criteria. The subroutine UVINIT will then be called again to determine the initial solution values at the new mesh points (there is no interpolation at this stage) and the integration proceeds.

The problem is subject to the following restrictions:

- (i) In (1), $\dot{V}_j(t)$, for j = 1, 2, ..., NCODE, may only appear **linearly** in the functions S_i , for i = 1, 2, ..., NPDE, with a similar restriction for G_i^L and G_i^R ;
- (ii) $P_{i,j}$, F_i , C_i and S_i must not depend on any space derivatives; and $P_{i,j}$, C_i , D_i and F_i must not depend on any time derivatives;
- (iii) $t_0 < t_{out}$, so that integration is in the forward direction;
- (iv) The evaluation of the terms $P_{i,j}$, C_i , D_i and S_i is done by calling the routine PDEDEF at a point approximately midway between each pair of mesh points in turn. Any discontinuities in these functions **must** therefore be at one or more of the **fixed** mesh points specified by XFIX;
- (v) At least one of the functions $P_{i,j}$ must be non-zero so that there is a time derivative present in the PDE problem.

For further details of the scheme, see Pennington and Berzins (1994) and the references therein.

4 References

Berzins M, Dew P M and Furzeland R M (1989) Developing software for time-dependent problems using the method of lines and differential-algebraic integrators *Appl. Numer. Math.* **5** 375–397

Furzeland R M (1984) The construction of adaptive space meshes *TNER.85.022* Thornton Research Centre, Chester

Hirsch C (1990) Numerical Computation of Internal and External Flows, Volume 2: Computational Methods for Inviscid and Viscous Flows John Wiley

LeVeque R J (1990) Numerical Methods for Conservation Laws Birkhäuser Verlag

Pennington S V and Berzins M (1994) New NAG Library software for first-order partial differential equations ACM Trans. Math. Softw. 20 63–99

Roe P L (1981) Approximate Riemann solvers, parameter vectors, and difference schemes J. Comput. Phys. 43 357-372

5 Parameters

1: NPDE – INTEGER

On entry: the number of PDEs to be solved.

Constraint: NPDE ≥ 1 .

2: TS – *real*

On entry: the initial value of the independent variable t.

Input/Output

On exit: the value of t corresponding to the solution values in U. Normally TS = TOUT. Constraint: TS < TOUT.

3: TOUT – *real*

On entry: the final value of t to which the integration is to be carried out.

4: PDEDEF – SUBROUTINE, supplied by the user.

PDEDEF must evaluate the functions $P_{i,j}$, C_i , D_i and S_i which partially define the system of PDEs. $P_{i,j}$ and C_i may depend on x, t, U and V; D_i may depend on x, t, U, U_x and V; and S_i may depend on x, t, U, V and linearly on \dot{V} . PDEDEF is called approximately midway between each pair of mesh points in turn by D03PSF. The actual argument D03PLP may be used for PDEDEF for problems in the form (2) (D03PLP is included in the NAG Fortran Library; however, its name may be implementation-dependent: see the Users' Note for your implementation for details).

Its specification is:

	SUBROUTINE PDEDEF(NPDE, T, X, U, UX, NCODE, V, VDOT, P, C, D, S, 1 IRES)
	INTEGERNPDE, NCODE, IRESrealT, X, U(NPDE), UX(NPDE), V(*), VDOT(*),1P(NPDE, NPDE), C(NPDE), D(NPDE), S(NPDE)
1:	NPDE – INTEGER Input
	On entry: the number of PDEs in the system.
2:	T – real Input
	On entry: the current value of the independent variable t .
3:	X – real Input
	On entry: the current value of the space variable x .
4:	U(NPDE) – <i>real</i> array Input
	On entry: U(i) contains the value of the component $U_i(x,t)$, for $i = 1, 2,, NPDE$.
5:	UX(NPDE) – <i>real</i> array Input
	On entry: UX(i) contains the value of the component $\partial U_i(x,t)/\partial x$, for $i = 1, 2,, NPDE$.
6:	NCODE – INTEGER Input
	On entry: the number of coupled ODEs in the system.
7:	V(*) – <i>real</i> array Input
	On entry: $V(i)$ contains the value of component $V_i(t)$, for $i = 1, 2,, NCODE$.
8:	VDOT(*) – <i>real</i> array Input
	On entry: VDOT(i) contains the value of component $\dot{\mathbf{V}}_i(t)$, for $i = 1, 2, \dots, \text{NCODE}$.
	Note: $\dot{\mathbf{V}}_i(t)$, for $i = 1, 2,, NCODE$, may only appear linearly in S_j , for $j = 1, 2,, NPDE$.
9:	P(NPDE,NPDE) – <i>real</i> array Output
	On exit: $P(i, j)$ must be set to the value of $P_{i,j}(x, t, U, V)$, for $i, j = 1, 2,, NPDE$.

Input

External Procedure

10: C(NPDE) - real array Output On exit: C(i) must be set to the value of $C_i(x, t, U, V)$, for i = 1, 2, ..., NPDE. D(NPDE) - real array Output 11: On exit: D(i) must be set to the value of $D_i(x, t, U, U_x, V)$, for i = 1, 2, ..., NPDE. 12: S(NPDE) – *real* array Output On exit: S(i) must be set to the value of $S_i(x, t, U, V, \dot{V})$, for i = 1, 2, ..., NPDE. **IRES - INTEGER** 13: Input/Output On entry: set to -1 or 1. On exit: should usually remain unchanged. However, the user may set IRES to force the integration routine to take certain actions as described below: IRES = 2indicates to the integrator that control should be passed back immediately to the calling (sub)program with the error indicator set to IFAIL = 6.

IRES = 3

indicates to the integrator that the current time step should be abandoned and a smaller time step used instead. The user may wish to set IRES = 3 when a physically meaningless input or output value has been generated. If the user consecutively sets IRES = 3, then D03PSF returns to the calling (sub)program with the error indicator set to IFAIL = 4.

PDEDEF must be declared as EXTERNAL in the (sub)program from which D03PSF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

5: NUMFLX – SUBROUTINE, supplied by the user.

External Procedure

NUMFLX must supply the numerical flux for each PDE given the *left* and *right* values of the solution vector U. NUMFLX is called approximately midway between each pair of mesh points in turn by D03PSF.

Its specification is:

	SUBROUTINE NUMFLX(NPDE, T, X, NCODE, V, ULEFT, URIGHT, FLUX, IRIINTEGERNPDE, NCODE, IRESrealT, X, V(*), ULEFT(NPDE), URIGHT(NPDE), FLUX(NI	
1:	NPDE – INTEGER	Input
	On entry: the number of PDEs in the system.	
2:	T – real	Input
	On entry: the current value of the independent variable t .	
3:	X – real	Input
	On entry: the current value of the space variable x .	
4:	NCODE – INTEGER	Input
	On entry: the number of coupled ODEs in the system.	
5:	V(*) – <i>real</i> array	Input
	On entry: $V(i)$ contains the value of the component $V_i(t)$, for $i = 1, 2,, NCOI$	DE.

D03PSF

6: ULEFT(NPDE) - real array Input On entry: ULEFT(i) contains the left value of the component $U_i(x)$, for i = 1, 2, ..., NPDE.7: URIGHT(NPDE) - *real* array Input On entry: URIGHT(i) contains the right value of the component $U_i(x)$, for i = 1, 2, ..., NPDE.FLUX(NPDE) - real array 8: Output On exit: FLUX(i) must be set to the numerical flux \hat{F}_i , for i = 1, 2, ..., NPDE. 9: **IRES – INTEGER** Input/Output On entry: set to -1 or 1. On exit: should usually remain unchanged. However, the user may set IRES to force the integration routine to take certain actions as described below: IRES = 2indicates to the integrator that control should be passed back immediately to the calling (sub)program with the error indicator set to IFAIL = 6. IRES = 3indicates to the integrator that the current time step should be abandoned and a smaller time step used instead. The user may wish to set IRES = 3 when a physically meaningless input or output value has been generated. If the user consecutively sets IRES = 3, then D03PSF returns to the calling (sub)program with the error indicator set to IFAIL = 4.

NUMFLX must be declared as EXTERNAL in the (sub)program from which D03PSF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

6: BNDARY – SUBROUTINE, supplied by the user.

External Procedure

BNDARY must evaluate the functions G_i^L and G_i^R which describe the physical and numerical boundary conditions, as given by (8) and (9).

Its specification is:

SUBROUTINE BNDARY(NPDE, NPTS, T, X, U, NCODE, V, VDOT, IBND, G, 1 IRES) NPDE, NPTS, NCODE, IBND, IRES INTEGER real T, X(NPTS), U(NPDE, NPTS), V(*), VDOT(*), G(NPDE) 1: NPDE – INTEGER Input On entry: the number of PDEs in the system. 2: NPTS - INTEGER Input On entry: the number of mesh points in the interval [a, b]. T – real 3: Input On entry: the current value of the independent variable t. X(NPTS) - *real* array 4: Input On entry: the mesh points in the spatial direction. X(1) corresponds to the left-hand boundary, a, and X(NPTS) corresponds to the right-hand boundary, b.

5:	U(NPDE,NPTS) – <i>real</i> array Input
	On entry: $U(i, j)$ contains the value of the component $U_i(x, t)$ at $x = X(j)$ for $i = 1, 2,, NPDE$; $j = 1, 2,, NPTS$.
	Note: if banded matrix algebra is to be used then the functions G_i^L and G_i^R may depend on the value of $U_i(x,t)$ at the boundary point and the two adjacent points only.
6:	NCODE – INTEGER Input
	On entry: the number of coupled ODEs in the system.
7:	V(*) – <i>real</i> array Input
	On entry: $V(i)$ contains the value of component $V_i(t)$, for $i = 1, 2,, NCODE$.
8:	VDOT(*) – <i>real</i> array Input
	On entry: VDOT(i) contains the value of component $\dot{\mathbf{V}}_i(t)$, for $i = 1, 2, \dots, \text{NCODE}$.
	Note: $\dot{\mathbf{V}}_i(t)$, for $i = 1, 2,, \text{NCODE}$, may only appear linearly in G_j^L and G_j^R , for $j = 1, 2,, \text{NPDE}$.
9:	IBND – INTEGER Input
	On entry: specifies which boundary conditions are to be evaluated. If IBND = 0, then BNDARY must evaluate the left-hand boundary condition at $x = a$. If IBND $\neq 0$, then BNDARY must evaluate the right-hand boundary condition at $x = b$.
10:	G(NPDE) – <i>real</i> array Output
	On exit: $G(i)$ must contain the <i>i</i> th component of either G_i^L or G_i^R in (8) and (9), depending on the value of IBND, for $i = 1, 2,, NPDE$.
11:	IRES – INTEGER Input/Output
	On entry: set to -1 or 1.
	<i>On exit</i> : should usually remain unchanged. However, the user may set IRES to force the integration routine to take certain actions as described below:
	IRES = 2
	indicates to the integrator that control should be passed back immediately to the calling (sub)program with the error indicator set to $IFAIL = 6$.
	IRES = 3
	indicates to the integrator that the current time step should be abandoned and a smaller time step used instead. The user may wish to set $IRES = 3$ when a physically meaningless input or output value has been generated. If the user consecutively sets $IRES = 3$, then D03PSF returns to the calling (sub)program with

BNDARY must be declared as EXTERNAL in the (sub)program from which D03PSF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

7: UVINIT – SUBROUTINE, supplied by the user. External Procedure UVINIT = SUBROUTINE, supplied by the user. External Procedure

the error indicator set to IFAIL = 4.

UVINIT must supply the initial $(t = t_0)$ values of U(x, t) and V(t) for all values of x in the interval $a \le x \le b$.

Its specification is:

	SUBROUTINE UVINIT(NPDE, NPTS, NXI, X, XI, U, NCODE, V)INTEGERNPDE, NPTS, NXI, NCODErealX(NPTS), XI(*), U(NPDE,NPTS), V(*)	
1:	NPDE – INTEGER	Input
	On entry: the number of PDEs in the system.	
2:	NPTS – INTEGER	Input
	On entry: the number of mesh points in the interval $[a, b]$.	
3:	NXI – INTEGER	Input
	On entry: the number of ODE/PDE coupling points.	
4:	X(NPTS) – <i>real</i> array	Input
	On entry: the current mesh. $X(i)$ contains the value of x_i for $i = 1, 2,, NPT$	S.
5:	XI(*) – <i>real</i> array	Input
	On entry: XI(i) contains the ODE/PDE coupling point, ξ_i , for $i = 1, 2,, NXI$.	
6:	U(NPDE,NPTS) – <i>real</i> array	Output
	On exit: $U(i, j)$ must contain the value of component $U_i(x_j, t_0)$ for $i = 1, 2,, j = 1, 2,, NPTS$.	, NPDE;
7:	NCODE – INTEGER	Input
	On entry: the number of coupled ODEs in the system.	
8:	V(*) – <i>real</i> array	Output
	On exit: $V(i)$ must contain the value of component $V_i(t_0)$ for $i = 1, 2,, NCOP$	DE.

UVINIT must be declared as EXTERNAL in the (sub)program from which D03PSF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

8: U(NEQN) – *real* array

On exit: U(NPDE × (j - 1) + i) contains the computed solution $U_i(x_j, t)$, for i = 1, 2, ..., NPDE; j = 1, 2, ..., NPTS, and U(NPTS × NPDE + k) contains $V_k(t)$, for k = 1, 2, ..., NCODE, all evaluated at t = TS.

9: NPTS – INTEGER

On entry: the number of mesh points in the interval [a, b].

Constraint: NPTS \geq 3.

10: X(NPTS) - real array

On entry: the mesh points in the space direction. X(1) must specify the left-hand boundary, a, and X(NPTS) must specify the right-hand boundary, b.

Constraint: $X(1) < X(2) < \ldots < X(NPTS)$.

11: NCODE – INTEGER

On entry: the number of coupled ODE components. *Constraint*: NCODE ≥ 0 . Output

Input

Input

12: ODEDEF – SUBROUTINE, supplied by the user.

External Procedure

ODEDEF must evaluate the functions R, which define the system of ODEs, as given in (4). If the user wishes to compute the solution of a system of PDEs only (i.e., NCODE = 0), ODEDEF must be the dummy routine D03PEK. (D03PEK is included in the NAG Fortran Library; however, its name may be implementation-dependent: see the Users' Note for your implementation for details.)

Its specification is:

SUBROUTINE ODEDEF(NPDE, T, NCODE, V, VDOT, NXI, XI, UCP, UCPX, UCPT, 1 R, IRES) NPDE, NCODE, NXI, IRES INTEGER T, V(*), VDOT(*), XI(*), UCP(NPDE,*), real 1 UCPX(NPDE,*), UCPT(NPDE,*), R(*) NPDE - INTEGER 1: Input On entry: the number of PDEs in the system. T – real 2: Input On entry: the current value of the independent variable t. 3: NCODE - INTEGER Input On entry: the number of coupled ODEs in the system. V(*) - real array 4: Input On entry: V(i) contains the value of component $V_i(t)$, for i = 1, 2, ..., NCODE. VDOT(*) - *real* array 5: Input On entry: VDOT(i) contains the value of component $\dot{V}_i(t)$, for $i = 1, 2, \dots$, NCODE. 6: NXI - INTEGER Input On entry: the number of ODE/PDE coupling points. 7: XI(*) – *real* array Input On entry: XI(i) contains the ODE/PDE coupling point, ξ_i , for i = 1, 2, ..., NXI. 8: UCP(NPDE,*) - *real* array Input On entry: UCP(i, j) contains the value of $U_i(x, t)$ at the coupling point $x = \xi_i$, for $i = 1, 2, \dots, \text{NPDE}; j = 1, 2, \dots, \text{NXI}.$ 9: UCPX(NPDE,*) - real array Input On entry: UCPX(i, j) contains the value of $\partial U_i(x, t)/\partial x$ at the coupling point $x = \xi_i$, for $i = 1, 2, \dots, NPDE; j = 1, 2, \dots, NXI.$ UCPT(NPDE,*) - *real* array 10: Input On entry: UCPT(i, j) contains the value of $\partial U_i(x, t)/\partial t$ at the coupling point $x = \xi_i$, for $i = 1, 2, \dots, NPDE; j = 1, 2, \dots, NXI.$ 11: R(*) - real array Output On exit: R(i) must contain the *i*th component of R, for i = 1, 2, ..., NCODE, where R is defined as $R = L - M\dot{V} - NU_t^*.$ (10)

or

$$R = -M\dot{V} - NU_t^*. \tag{11}$$

The definition of R is determined by the input value of IRES.

12: IRES – INTEGER

Input/Output

On entry: the form of R that must be returned in the array R. If IRES = 1, then the equation (10) above must be used. If IRES = -1, then the equation (11) above must be used.

On exit: should usually remain unchanged. However, the user may reset IRES to force the integration routine to take certain actions as described below:

IRES = 2

indicates to the integrator that control should be passed back immediately to the calling (sub)program with the error indicator set to IFAIL = 6.

IRES = 3

indicates to the integrator that the current time step should be abandoned and a smaller time step used instead. The user may wish to set IRES = 3 when a physically meaningless input or output value has been generated. If the user consecutively sets IRES = 3, then D03PSF returns to the calling (sub)program with the error indicator set to IFAIL = 4.

ODEDEF must be declared as EXTERNAL in the (sub)program from which D03PSF is called. Parameters denoted as *Input* must **not** be changed by this procedure.

13: NXI – INTEGER

On entry: the number of ODE/PDE coupling points.

Constraints:

NXI = 0 if NCODE = 0, NXI \geq 0 if NCODE > 0.

14: XI(*) – *real* array

On entry: XI(*i*), i = 1, 2, ..., NXI, must be set to the ODE/PDE coupling points. *Constraint*: X(1) \leq XI(1) < XI(2) < ... < XI(NXI) \leq X(NPTS).

15: NEQN – INTEGER

On entry: the number of ODEs in the time direction. *Constraint*: NEQN = NPDE \times NPTS + NCODE.

16: RTOL(*) – *real* array

Note: the dimension of the array RTOL must be at least 1 if ITOL = 1 or 2 and at least NEQN if ITOL = 3 or 4.

On entry: the relative local error tolerance.

Constraint: $RTOL(i) \ge 0.0$ for all relevant *i*.

17: ATOL(*) – *real* array

Note: the dimension of the array ATOL must be at least 1 if ITOL = 1 or 3 and at least NEQN if ITOL = 2 or 4.

On entry: the absolute local error tolerance.

Constraint: ATOL $(i) \ge 0.0$ for all relevant *i*.

Input

Input

Input

Input

18: ITOL – INTEGER

Input

Input

On entry: a value to indicate the form of the local error test. If e_i is the estimated local error for U(i), i = 1, 2, ..., NEQN, and $\| \|$ denotes the norm, then the error test to be satisfied is $\|e_i\| < 1.0$. ITOL indicates to D03PSF whether to interpret either or both of RTOL and ATOL as a vector or scalar in the formation of the weights w_i used in the calculation of the norm (see the description of the parameter NORM below):

ITOL	RTOL	ATOL	w_i
1			$RTOL(1) \times U(i) + ATOL(1)$
2			$\operatorname{RTOL}(1) \times \operatorname{U}(i) + \operatorname{ATOL}(i)$
3			$\operatorname{RTOL}(i) \times \operatorname{U}(i) + \operatorname{ATOL}(1)$
4	vector	vector	$\operatorname{RTOL}(i) \times \operatorname{U}(i) + \operatorname{ATOL}(i)$

Constraint: $1 \leq \text{ITOL} \leq 4$.

19: NORM – CHARACTER*1

On entry: the type of norm to be used. Two options are available:

'1' – averaged L_1 norm.

'2' – averaged L_2 norm.

If $U_{\rm norm}$ denotes the norm of the vector U of length NEQN, then for the averaged L_1 norm

$$U_{\text{norm}} = \frac{1}{\text{NEQN}} \sum_{i=1}^{\text{NEQN}} U(i) / w_i,$$

and for the averaged L_2 norm

$$U_{\text{norm}} = \sqrt{\frac{1}{\text{NEQN}} \sum_{i=1}^{\text{NEQN}} (\mathbf{U}(i)/w_i)^2},$$

See the description of parameter ITOL for the formulation of the weight vector w. Constraint: NORM = '1' or '2'.

20: LAOPT – CHARACTER*1

On entry: the type of matrix algebra required. The possible choices are:

'F' - full matrix routines to be used;

'B' - banded matrix routines to be used;

'S' - sparse matrix routines to be used.

Constraint: LAOPT = 'F', 'B' or 'S'.

Note: the user is recommended to use the banded option when no coupled ODEs are present (NCODE = 0). Also, the banded option should not be used if the boundary conditions involve solution components at points other than the boundary and the immediately adjacent two points.

21: ALGOPT(30) - *real* array

On entry: ALGOPT may be set to control various options available in the integrator. If the user wishes to employ all the default options, then ALGOPT(1) should be set to 0.0. Default values will also be used for any other elements of ALGOPT set to zero. The permissible values, default values, and meanings are as follows:

ALGOPT(1) selects the ODE integration method to be used. If ALGOPT(1) = 1.0, a BDF method is used and if ALGOPT(1) = 2.0, a Theta method is used.

The default is ALGOPT(1) = 1.0.

If ALGOPT(1) = 2.0, then ALGOPT(i), for i = 2, 3, 4 are not used.

Input

ALGOPT(2) specifies the maximum order of the BDF integration formula to be used. ALGOPT(2) may be 1.0, 2.0, 3.0, 4.0 or 5.0.

The default value is ALGOPT(2) = 5.0.

ALGOPT(3) specifies what method is to be used to solve the system of nonlinear equations arising on each step of the BDF method. If ALGOPT(3) = 1.0 a modified Newton iteration is used and if ALGOPT(3) = 2.0 a functional iteration method is used. If functional iteration is selected and the integrator encounters difficulty, then there is an automatic switch to the modified Newton iteration.

The default value is ALGOPT(3) = 1.0.

ALGOPT(4) specifies whether or not the Petzold error test is to be employed. The Petzold error test results in extra overhead but is more suitable when algebraic equations are present, such as $P_{i,j} = 0.0$, for j = 1, 2, ..., NPDE for some *i* or when there is no $\dot{V}_i(t)$ dependence in the coupled ODE system. If ALGOPT(4) = 1.0, then the Petzold test is used. If ALGOPT(4) = 2.0, then the Petzold test is not used.

The default value is ALGOPT(4) = 1.0.

If ALGOPT(1) = 1.0, then ALGOPT(i), for i = 5, 6, 7 are not used.

ALGOPT(5), specifies the value of Theta to be used in the Theta integration method.

 $0.51 \le ALGOPT(5) \le 0.99.$

The default value is ALGOPT(5) = 0.55.

ALGOPT(6) specifies what method is to be used to solve the system of nonlinear equations arising on each step of the Theta method. If ALGOPT(6) = 1.0, a modified Newton iteration is used and if ALGOPT(6) = 2.0, a functional iteration method is used.

The default value is ALGOPT(6) = 1.0.

ALGOPT(7) specifies whether or not the integrator is allowed to switch automatically between modified Newton and functional iteration methods in order to be more efficient. If ALGOPT(7) = 1.0, then switching is allowed and if ALGOPT(7) = 2.0, then switching is not allowed.

The default value is ALGOPT(7) = 1.0.

ALGOPT(11) specifies a point in the time direction, t_{crit} , beyond which integration must not be attempted. The use of t_{crit} is described under the parameter ITASK. If ALGOPT(1) $\neq 0.0$, a value of 0.0 for ALGOPT(11), say, should be specified even if ITASK subsequently specifies that t_{crit} will not be used.

ALGOPT(12) specifies the minimum absolute step size to be allowed in the time integration. If this option is not required, ALGOPT(12) should be set to 0.0.

ALGOPT(13) specifies the maximum absolute step size to be allowed in the time integration. If this option is not required, ALGOPT(13) should be set to 0.0.

ALGOPT(14) specifies the initial step size to be attempted by the integrator. If ALGOPT(14) = 0.0, then the initial step size is calculated internally.

ALGOPT(15) specifies the maximum number of steps to be attempted by the integrator in any one call. If ALGOPT(15) = 0.0, then no limit is imposed.

ALGOPT(23) specifies what method is to be used to solve the nonlinear equations at the initial point to initialise the values of U, U_t , V and \dot{V} . If ALGOPT(23) = 1.0, a modified Newton iteration is used and if ALGOPT(23) = 2.0, functional iteration is used.

The default value is ALGOPT(23) = 1.0.

ALGOPT(29) and ALGOPT(30) are used only for the sparse matrix algebra option, i.e., LAOPT = S'.

ALGOPT(29) governs the choice of pivots during the decomposition of the first Jacobian matrix. It should lie in the range 0.0 < ALGOPT(29) < 1.0, with smaller values biasing the algorithm

towards maintaining sparsity at the expense of numerical stability. If ALGOPT(29) lies outside the range then the default value is used. If the routines regard the Jacobian matrix as numerically singular, then increasing ALGOPT(29) towards 1.0 may help, but at the cost of increased fill-in.

The default value is ALGOPT(29) = 0.1.

ALGOPT(30) is used as the relative pivot threshold during subsequent Jacobian decompositions (see ALGOPT(29)) below which an internal error is invoked. ALGOPT(30) must be greater than zero, otherwise the default value is used. If ALGOPT(30) is greater than 1.0 no check is made on the pivot size, and this may be a necessary option if the Jacobian matrix is found to be numerically singular (see ALGOPT(29)).

The default value is ALGOPT(30) = 0.0001.

22: REMESH – LOGICAL

On entry: indicates whether or not spatial remeshing should be performed.

REMESH = .TRUE. indicates that spatial remeshing should be performed as specified.

REMESH = .FALSE. indicates that spatial remeshing should be suppressed.

Note: REMESH should **not** be changed between consecutive calls to D03PSF. Remeshing can be switched off or on at specified times by using appropriate values for the parameters NRMESH and TRMESH at each call.

23: NXFIX – INTEGER

On entry: the number of fixed mesh points.

Constraint: $0 \leq \text{NXFIX} \leq \text{NPTS} - 2$.

Note: the end-points X(1) and X(NPTS) are fixed automatically and hence should not be specified as fixed points.

24: XFIX(*) – *real* array

Note: the dimension of the array XFIX must be at least max(1, NXFIX).

On entry: XFIX(i), i = 1, 2, ..., NXFIX, must contain the value of the x coordinate at the *i*th fixed mesh point.

Constraint: XFIX(i) < XFIX(i + 1), i = 1, 2, ..., NXFIX - 1, and each fixed mesh point must coincide with a user-supplied initial mesh point, that is XFIX(i) = X(j) for some j, $2 \le j \le NPTS - 1$.

Note: the positions of the fixed mesh points in the array X(NPTS) remain fixed during remeshing, and so the number of mesh points between adjacent fixed points (or between fixed points and endpoints) does not change. The user should take this into account when choosing the initial mesh distribution.

25: NRMESH – INTEGER

On entry: specifies the spatial remeshing frequency and criteria for the calculation and adoption of a new mesh.

NRMESH < 0

indicates that a new mesh is adopted according to the parameter DXMESH below. The mesh is tested every |NRMESH| timesteps.

NRMESH = 0

indicates that remeshing should take place just once at the end of the first time step reached when t > TRMESH (see below).

Input

Input

Input

indicates that remeshing will take place every NRMESH time steps, with no testing using DXMESH.

Note: NRMESH may be changed between consecutive calls to D03PSF to give greater flexibility over the times of remeshing.

26: DXMESH – real

On entry: determines whether a new mesh is adopted when NRMESH is set less than zero. A possible new mesh is calculated at the end of every [NRMESH] time steps, but is adopted only if

$$x_i^{(\text{new})} > x_i^{(\text{old})} + \text{DXMESH} \times (x_{i+1}^{(\text{old})} - x_i^{(\text{old})})$$

or

$$x_i^{(\text{new})} < x_i^{(\text{old})} - \text{DXMESH} \times (x_i^{(\text{old})} - x_{i-1}^{(\text{old})})$$

DXMESH thus imposes a lower limit on the difference between one mesh and the next. *Constraint*: DXMESH \geq 0.0.

27: TRMESH – *real*

On entry: specifies when remeshing will take place when NRMESH is set to zero. Remeshing will occur just once at the end of the first time step reached when t is greater than TRMESH.

Note: TRMESH may be changed between consecutive calls to D03PSF to force remeshing at several specified times.

28: IPMINF – INTEGER

On entry: the level of trace information regarding the adaptive remeshing. Details are directed to the current advisory message unit (see X04ABF).

IPMINF = 0

No trace information.

IPMINF = 1

Brief summary of mesh characteristics.

IPMINF = 2

More detailed information, including old and new mesh points, mesh sizes and monitor function values.

Constraint: $0 \leq \text{IPMINF} \leq 2$.

29: XRATIO – real

On entry: an input bound on the adjacent mesh ratio (greater than 1.0 and typically in the range 1.5 to 3.0). The remeshing routines will attempt to ensure that

$$(x_i - x_{i-1})$$
/XRATIO $< x_{i+1} - x_i <$ XRATIO $\times (x_i - x_{i-1})$

Suggested value: XRATIO = 1.5.

Constraint: XRATIO > 1.0.

30: CONST – *real*

On entry: an input bound on the sub-integral of the monitor function $F^{\text{mon}}(x)$ over each space step. The remeshing routines will attempt to ensure that

$$\int_{x_i}^{x_{i+1}} F^{\text{mon}}(x) dx \le \text{CONST} \int_{x_1}^{x_{\text{NPTS}}} F^{\text{mon}}(x) dx,$$

Input

Input

Input

(see Furzeland (1984)). CONST gives the user more control over the mesh distribution e.g., decreasing CONST allows more clustering. A typical value is 2/(NPTS - 1), but the user is encouraged to experiment with different values. Its value is not critical and the mesh should be qualitatively correct for all values in the range given below.

Suggested value: CONST = 2.0/(NPTS - 1). *Constraint*: $0.1/(\text{NPTS} - 1) \leq \text{CONST} \leq 10.0/(\text{NPTS} - 1)$.

31: MONITF - SUBROUTINE, supplied by the user. External Procedure

MONITF must supply and evaluate a remesh monitor function to indicate the solution behaviour of interest.

If the user specifies REMESH = .FALSE., i.e., no remeshing, then MONITF will not be called and the dummy routine D03PEL may be used for MONITF. (D03PEL is included in the NAG Fortran Library; however, its name may be implementation-dependent: see the Users' Note for your implementation for details.)

Its specification is:

	SUBROUTINE MONITF(T, NPTS, NPDE, X, U, FMON)INTEGERNPTS, NPDErealT, X(NPTS), U(NPDE,NPTS), FMON(NPTS)	
1:	T – real	Input
	On entry: the current value of the independent variable t.	
2:	NPTS – INTEGER	Input
	On entry: the number of mesh points in the interval $[a, b]$.	
3:	NPDE – INTEGER	Input
	On entry: the number of PDEs in the system.	
4:	X(NPTS) – <i>real</i> array	Input
	On entry: the current mesh. $X(i)$ contains the value of x_i for $i = 1, 2,, NPTS$.	
5:	U(NPDE,NPTS) – <i>real</i> array	Input
	On entry: $U(i, j)$ contains the value of component $U_i(x, t)$ at $x = X(j)$ and time $i = 1, 2,, NPDE$, $j = 1, 2,, NPTS$.	t, for
6:	FMON(NPTS) – <i>real</i> array	Dutput
	On exit: FMON(i) must contain the value of the monitor function $F^{\text{mon}}(x)$ at mesh $x = X(i)$.	point
	Constraint: $FMON(i) \ge 0$.	

MONITF must be declared as EXTERNAL in the (sub)program from which D03PSF is called. Parameters denoted as *Input* must not be changed by this procedure.

32:	W(NW) – <i>real</i> array	Workspace
33:	NW – INTEGER	Input

On entry: the dimension of the array W as declared in the (sub)program from which D03PSF is called. Its size depends on the type of matrix algebra selected:

LAOPT = 'F',

 $NW \ge NEQN \times NEQN + NEQN + NWKRES + LENODE$,

LAOPT = 'B',

 $NW \ge (3 \times MLU + 1) \times NEQN + NWKRES + LENODE,$

LAOPT = 'S',

 $NW \ge 4 \times NEQN + 11 \times NEQN/2 + 1 + NWKRES + LENODE,$

where MLU = the lower or upper half bandwidths, and

 $MLU = 3 \times NPDE - 1$, for PDE problems only, and,

MLU = NEQN - 1, for coupled PDE/ODE problems.

 $\begin{aligned} \text{NWKRES} &= \text{NPDE} \times (2 \times \text{NPTS} + 6 \times \text{NXI} + 3 \times \text{NPDE} + 26) + \text{NXI} + \text{NCODE} + \\ 7 \times \text{NPTS} + \text{NXFIX} + 1 \end{aligned}$

when NCODE > 0 and NXI > 0;

 $NWKRES = NPDE \times (2 \times NPTS + 3 \times NPDE + 32) + NCODE + 7 \times NPTS + NXFIX + 2$

when NCODE > 0 and NXI = 0;

NWKRES = NPDE \times (2 \times NPTS + 3 \times NPDE + 32) + 7 \times NPTS + NXFIX + 3

when NCODE = 0.

 $LENODE = (6 + int(ALGOPT(2))) \times NEQN + 50$, when the BDF method is used and,

LENODE = $9 \times NEQN + 50$, when the Theta method is used.

Note: when LAOPT = 'S', the value of NW may be too small when supplied to the integrator. An estimate of the minimum size of NW is printed on the current error message unit if ITRACE > 0 and the routine returns with IFAIL = 15.

34: IW(NIW) – INTEGER array

On exit: the following components of the array IW concern the efficiency of the integration.

IW(1) contains the number of steps taken in time.

IW(2) contains the number of residual evaluations of the resulting ODE system used. One such evaluation involves evaluating the PDE functions at all the mesh points, as well as one evaluation of the functions in the boundary conditions.

IW(3) contains the number of Jacobian evaluations performed by the time integrator.

IW(4) contains the order of the BDF method last used in the time integration, if applicable. When the Theta method is used IW(4) contains no useful information.

IW(5) contains the number of Newton iterations performed by the time integrator. Each iteration involves residual evaluation of the resulting ODE system followed by a back-substitution using the LU decomposition of the Jacobian matrix.

35: NIW – INTEGER

Input

Output

On entry: the dimension of the array IW. Its size depends on the type of matrix algebra selected: LAOPT = F',

NIW \geq 25,

LAOPT = 'B',

NIW \geq NEQN + NXFIX + 25,

LAOPT = 'S',

 $NIW \ge 25 \times NEQN + NXFIX + 25.$

Note: when LAOPT = 'S', the value of NIW may be too small when supplied to the integrator. An estimate of the minimum size of NIW is printed on the current error message unit if ITRACE > 0 and the routine returns with IFAIL = 15.

36: ITASK – INTEGER

Input

On entry: the task to be performed by the ODE integrator. The permitted values of ITASK and their meanings are detailed below:

ITASK = 1

normal computation of output values U at t = TOUT (by overshooting and interpolating).

ITASK = 2

take one step in the time direction and return.

ITASK = 3

stop at first internal integration point at or beyond t = TOUT.

ITASK = 4

normal computation of output values U at t = TOUT but without overshooting $t = t_{\text{crit}}$ where t_{crit} is described under the parameter ALGOPT.

ITASK = 5

take one step in the time direction and return, without passing t_{crit} , where t_{crit} is described under the parameter ALGOPT.

Constraint: $1 \leq ITASK \leq 5$.

37: ITRACE – INTEGER

On entry: the level of trace information required from D03PSF and the underlying ODE solver. ITRACE may take the value -1, 0, 1, 2, or 3. If ITRACE < -1, then -1 is assumed and similarly if ITRACE > 3, then 3 is assumed. If ITRACE = -1, no output is generated. If ITRACE = 0, only warning messages from the PDE solver are printed on the current error message unit (see X04AAF). If ITRACE > 0, then output from the underlying ODE solver is printed on the current advisory message unit (see X04ABF). This output contains details of Jacobian entries, the nonlinear iteration and the time integration during the computation of the ODE system. The advisory messages are given in greater detail as ITRACE increases. Users are advised to set ITRACE = 0, unless they are experienced with the sub-chapter D02M–N of the NAG Fortran Library.

On entry: IND must be set to 0 or 1.

$$IND = 0$$

starts or restarts the integration in time.

IND = 1

continues the integration after an earlier exit from the routine. In this case, only the parameters TOUT, IFAIL, NRMESH and TRMESH may be reset between calls to D03PSF.

Constraint: $0 \leq IND \leq 1$.

On exit: IND = 1.

39: IFAIL – INTEGER

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

Input/Output

Input/Output

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry,	$TS \ge TOUT$,
or	TOUT – TS is too small,
or	ITASK \neq 1, 2, 3, 4 or 5,
or	at least one of the coupling points defined in array XI is outside the interval
	[X(1),X(NPTS)],
or	the coupling points are not in strictly increasing order,
or	NPTS $<$ 3,
or	NPDE < 1 ,
or	LAOPT \neq 'F', 'B' or 'S',
or	ITOL \neq 1, 2, 3 or 4,
or	$IND \neq 0$ or 1,
or	incorrectly defined user mesh, i.e., $X(i) \ge X(i+1)$ for some $i = 1, 2,, NPTS - 1$,
or	NW or NIW are too small,
or	NCODE and NXI are incorrectly defined,
or	IND = 1 on initial entry to D03PSF,
or	NEQN \neq NPDE \times NPTS + NCODE,
or	an element of RTOL or ATOL < 0.0 ,
or	corresponding elements of RTOL and ATOL are both 0.0,
or	NORM \neq '1' or '2',
or	NXFIX not in the range 0 to NPTS -2 ,
or	fixed mesh point(s) do not coincide with any of the user-supplied mesh points,
or	DXMESH < 0.0,
or	IPMINF $\neq 0, 1$ or 2,
or	$XRATIO \leq 1.0,$
or	CONST not in the range $0.1/(NPTS - 1)$ to $10.0/(NPTS - 1)$.

IFAIL = 2

The underlying ODE solver cannot make any further progress, with the values of ATOL and RTOL, across the integration range from the current point t = TS. The components of U contain the computed values at the current point t = TS.

IFAIL = 3

In the underlying ODE solver, there were repeated error test failures on an attempted step, before completing the requested task, but the integration was successful as far as t = TS. The problem may have a singularity, or the error requirement may be inappropriate. Incorrect specification of boundary conditions may also result in this error.

IFAIL = 4

In setting up the ODE system, the internal initialisation routine was unable to initialise the derivative of the ODE system. This could be due to the fact that IRES was repeatedly set to 3 in one of the user-supplied subroutines PDEDEF, NUMFLX, BNDARY or ODEDEF, when the residual in the underlying ODE solver was being evaluated. Incorrect specification of boundary conditions may also result in this error.

IFAIL = 5

In solving the ODE system, a singular Jacobian has been encountered. Check the problem formulation.

IFAIL = 6

When evaluating the residual in solving the ODE system, IRES was set to 2 in at least one of the user-supplied subroutines PDEDEF, NUMFLX, BNDARY or ODEDEF. Integration was successful as far as t = TS.

IFAIL = 7

The values of ATOL and RTOL are so small that the routine is unable to start the integration in time.

IFAIL = 8

In one of the user-supplied routines, PDEDEF, NUMFLX, BNDARY or ODEDEF, IRES was set to an invalid value.

IFAIL = 9

A serious error has occurred in an internal call to D02NNF. Check problem specification and all parameters and array dimensions. Setting ITRACE = 1 may provide more information. If the problem persists, contact NAG.

IFAIL = 10

The required task has been completed, but it is estimated that a small change in ATOL and RTOL is unlikely to produce any change in the computed solution. (Only applies when the user is not operating in one step mode, that is when ITASK $\neq 2$ or 5.)

IFAIL = 11

An error occurred during Jacobian formulation of the ODE system (a more detailed error description may be directed to the current advisory message unit when $ITRACE \ge 1$). If using the sparse matrix algebra option, the values of ALGOPT(29) and ALGOPT(30) may be inappropriate.

IFAIL = 12

In solving the ODE system, the maximum number of steps specified in ALGOPT(15) has been taken.

IFAIL = 13

Some error weights w_i became zero during the time integration (see description of ITOL). Pure relative error control (ATOL(i) = 0.0) was requested on a variable (the *i*th) which has become zero. The integration was successful as far as t = TS.

IFAIL = 14

One or more of the functions $P_{i,j}$, D_i or C_i was detected as depending on time derivatives, which is not permissible.

IFAIL = 15

When using the sparse option, the value of NIW or NW was not sufficient (more detailed information may be directed to the current error message unit).

IFAIL = 16

REMESH has been changed between calls to D03PSF.

IFAIL = 17

FMON is negative at one or more mesh points, or zero mesh spacing has been obtained due to an inappropriate choice of monitor function.

7 Accuracy

The routine controls the accuracy of the integration in the time direction but not the accuracy of the approximation in space. The spatial accuracy depends on both the number of mesh points and on their distribution in space. In the time integration only the local error over a single step is controlled and so the accuracy over a number of steps cannot be guaranteed. The user should therefore test the effect of varying the accuracy parameters, ATOL and RTOL.

8 Further Comments

The routine is designed to solve systems of PDEs in conservative form, with optional source terms which are independent of space derivatives, and optional second-order diffusion terms. The use of the routine to solve systems which are not naturally in this form is discouraged, and users are advised to use one of the central-difference scheme routines for such problems.

Users should be aware of the stability limitations for hyperbolic PDEs. For most problems with small error tolerances the ODE integrator does not attempt unstable time steps, but in some cases a maximum time step should be imposed using ALGOPT(13). It is worth experimenting with this parameter, particularly if the integration appears to progress unrealistically fast (with large time steps). Setting the maximum time step to the minimum mesh size is a safe measure, although in some cases this may be too restrictive.

Problems with source terms should be treated with caution, as it is known that for large source terms stable and reasonable looking solutions can be obtained which are in fact incorrect, exhibiting non-physical speeds of propagation of discontinuities (typically one spatial mesh point per time step). It is essential to employ a very fine mesh for problems with source terms and discontinuities, and to check for non-physical propagation speeds by comparing results for different mesh sizes. Further details and an example can be found in Pennington and Berzins (1994).

The time taken by the routine depends on the complexity of the system, the accuracy requested, and the frequency of the mesh updates. For a given system with fixed accuracy and mesh-update frequency it is approximately proportional to NEQN.

9 Example

For this routine two examples are presented, in Section 9.1 of the documents for D03PSF and D03PSF. In the example programs distributed to sites, there is a single example program for D03PSF, with a main program:

```
DO3PSF Example Program Text
*
*
      Mark 18 Revised. NAG Copyright 1997.
      .. Parameters ..
*
      INTEGER
                       NOUT
     PARAMETER
                        (NOUT=6)
      .. External Subroutines ..
*
      EXTERNAL
                       EX1, EX2
      .. Executable Statements ..
      WRITE (NOUT, *) 'DO3PSF Example Program Results'
      CALL EX1
      CALL EX2
      STOP
     END
```

The code to solve the two example problems is given in the subroutines EX1 and EX2, in D03PSF and D03PSF respectively.

9.1 Example 1

This example is a simple model of the advection and diffusion of a cloud of material:

$$\frac{\partial U}{\partial t} + W \frac{\partial U}{\partial x} = C \frac{\partial^2 U}{\partial x^2},$$

for $x \in [0,1]$ and $t \le 0 \le 0.3$. In this example the constant wind speed W = 1 and the diffusion coefficient C = 0.002.

The cloud does not reach the boundaries during the time of integration, and so the two (physical) boundary conditions are simply U(0,t) = U(1,t) = 0.0, and the initial condition is

$$U(x,0) = \sin\Bigl(\pi\frac{x-a}{b-a}\Bigr), \text{for} \quad a \le x \le b,$$

and U(x, 0) = 0 elsewhere, where a = 0.2 and b = 0.4.

The numerical flux is simply $\hat{F} = WU_L$.

The monitor function for remeshing is taken to be the absolute value of the second derivative of U.

9.1.1 Program Text

Note: the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
SUBROUTINE EX1
      .. Parameters ..
*
      INTEGER
                         NOUT
      PARAMETER
                         (NOUT=6)
                         NPDE, NPTS, NCODE, NXI, NXFIX, NEQN, NIW, NWKRES,
      INTEGER
                         LENODE, MLU, NW, INTPTS, ITYPE
     +
      PARAMETER
                         (NPDE=1,NPTS=61,NCODE=0,NXI=0,NXFIX=0,
                         NEQN=NPDE*NPTS+NCODE,NIW=25+NXFIX+NEQN,
     +
                         NWKRES=NPDE*(3*NPTS+3*NPDE+32)+7*NPTS+3,
     +
     +
                         LENODE=11*NEQN+50,MLU=3*NPDE-1,NW=(3*MLU+1)
     +
                         *NEQN+NWKRES+LENODE, INTPTS=7, ITYPE=1)
      .. Scalars in Common ..
*
      real
                         Ρ
      .. Local Scalars .
*
                         CONST, DXMESH, TOUT, TRMESH, TS, XRATIO, XX
I, IFAIL, IND, IPMINF, IT, ITASK, ITOL, ITRACE,
      real
      INTEGER
                         M, NRMESH
     +
      LOGICAL
                         REMESH
      CHARACTER
                        LAOPT, NORM
      .. Local Arrays ..
*
      real
                         ALGOPT(30), ATOL(1), RTOL(1), U(NPDE, NPTS),
                         UOUT(NPDE, INTPTS, ITYPE), W(NW), X(NPTS), XFIX(1),
     +
                         XI(1), XOUT(INTPTS)
                         IW(NIW)
      INTEGER
      .. External Functions ..
*
      real
                        X01AAF
      EXTERNAL
                         X01AAF
      .. External Subroutines ..
*
                         BNDRY1, DO3PEK, DO3PSF, DO3PZF, MONIT1, NMFLX1,
      EXTERNAL
                         PDEF1, UVIN1
     +
      .. Common blocks ..
      COMMON
                         /PI/P
*
      .. Save statement ..
      SAVE
                         /PI/
*
      .. Data statements ..
                         XOUT(1)/0.2e+0/, XOUT(2)/0.3e+0/,
      DATA
                         XOUT(3)/0.4e+0/, XOUT(4)/0.5e+0/,
XOUT(5)/0.6e+0/, XOUT(6)/0.7e+0/, XOUT(7)/0.8e+0/
     +
      .. Executable Statements ..
*
      WRITE (NOUT, *)
      WRITE (NOUT, *)
      WRITE (NOUT, *)
                       'Example 1'
      WRITE (NOUT, *)
      XX = 0.0e0
      P = XO1AAF(XX)
      ITRACE = 0
      ITOL = 1
      NORM = '1'
      ATOL(1) = 0.1e-3
```

```
RTOL(1) = 0.1e-3
       WRITE (NOUT, 99998) NPTS, ATOL, RTOL
*
       Initialise mesh ..
*
       DO 20 I = 1, NPTS
          X(I) = (I-1.0e^{0}) / (NPTS-1.0e^{0})
   20 CONTINUE
       XFIX(1) = 0.0e0
       Set remesh parameters..
*
       REMESH = .TRUE.
       NRMESH = 3
       DXMESH = 0.0e^{0}
       TRMESH = 0.0e0
       CONST = 2.0e0/(NPTS-1.0e0)
       XRATIO = 1.5e^{0}
       IPMINF = 0
*
       XI(1) = 0.0e0
       LAOPT = 'B'
       IND = 0
       ITASK = 1
*
       DO 40 I = 1, 30
          ALGOPT(I) = 0.0e0
   40 CONTINUE
       b.d.f. integration
*
       ALGOPT(1) = 1.0e^{0}
       ALGOPT(13) = 0.5e-2
*
       Loop over output value of t
*
       TS = 0.0e0
       TOUT = 0.0e0
       DO 60 IT = 1, 3
          TOUT = IT*0.1e0
          IFAIL = 0
*
          CALL D03PSF(NPDE,TS,TOUT,PDEF1,NMFLX1,BNDRY1,UVIN1,U,NPTS,X,
                         NCODE, DO3PEK, NXI, XI, NEQN, RTOL, ATOL, ITOL, NORM, LAOPT,
      +
      +
                         ALGOPT, REMESH, NXFIX, XFIX, NRMESH, DXMESH, TRMESH,
      +
                         IPMINF, XRATIO, CONST, MONIT1, W, NW, IW, NIW, ITASK,
      +
                         ITRACE, IND, IFAIL)
*
          WRITE (NOUT,99999) TS
          WRITE (NOUT, 99996) (XOUT(I), I=1, INTPTS)
*
           Interpolate at output points ..
          M = 0
          CALL D03PZF(NPDE,M,U,NPTS,X,XOUT,INTPTS,ITYPE,UOUT,IFAIL)
*
          WRITE (NOUT, 99995) (UOUT(1,1,1), I=1, INTPTS)
   60 CONTINUE
*
       WRITE (NOUT, 99997) IW(1), IW(2), IW(3), IW(5)
       RETURN
*
99999 FORMAT (' T = ', F6.3)
99998 FORMAT (/' NPTS = ', I4, ' ATOL = ', e10.3, ' RTOL = ', e10.3, /)
99997 FORMAT (/ Number of integration steps in time = ',I6,/' Number ',
+ 'of function evaluations = ',I6,/' Number of Jacobian ',
+ 'evaluations = ',I6,/' Number of iterations = ',I6,/)
99996 FORMAT (1X,'X ',7F9.4)
99995 FORMAT (1X, 'Approx U ', 7F9.4,/)
       END
*
       SUBROUTINE UVIN1(NPDE, NPTS, NXI, X, XI, U, NCODE, V)
*
       .. Scalar Arguments ..
       INTEGER
                           NCODE, NPDE, NPTS, NXI
*
       .. Array Arguments ..
```

```
real
                       U(NPDE,NPTS), V(*), X(NPTS), XI(*)
      .. Scalars in Common ..
     real
                      P
     .. Local Scalars ..
*
     real
                       TMP
     INTEGER
                       I
      .. Intrinsic Functions ..
*
     INTRINSIC
                 SIN
      .. Common blocks ..
*
     COMMON /PI/P
      .. Save statement ..
*
     SAVE
                      /PI/
*
      .. Executable Statements ..
     DO 20 I = 1, NPTS
         IF (X(I).GT.0.2e0 .AND. X(I).LE.0.4e0) THEN
            TMP = P*(5.0e0*X(I)-1.0e0)
            U(1,I) = SIN(TMP)
         ELSE
            U(1,I) = 0.0e0
         END IF
   20 CONTINUE
      RETURN
     END
*
      SUBROUTINE PDEF1(NPDE,T,X,U,UX,NCODE,V,VDOT,P,C,D,S,IRES)
*
      .. Scalar Arguments ..
                       т, х
     real
      TNTEGER
                       IRES, NCODE, NPDE
      .. Array Arguments ..
*
                       C(NPDE), D(NPDE), P(NPDE,NPDE), S(NPDE), U(NPDE),
     real
                       UX(NPDE), V(*), VDOT(*)
     +
      .. Executable Statements ..
*
     P(1,1) = 1.0e0
     C(1) = 0.2e-2
     D(1) = UX(1)
     S(1) = 0.0e0
     RETURN
     END
*
      SUBROUTINE BNDRY1(NPDE,NPTS,T,X,U,NCODE,V,VDOT,IBND,G,IRES)
      .. Scalar Arguments ..
*
      real
                        Т
     INTEGER
                        IBND, IRES, NCODE, NPDE, NPTS
      .. Array Arguments ..
     real
                        G(NPDE), U(NPDE, NPTS), V(*), VDOT(*), X(NPTS)
      .. Executable Statements ..
      Zero solution at both boundaries
      IF (IBND.EQ.0) THEN
        G(1) = U(1,1)
      ELSE
         G(1) = U(1, NPTS)
     END IF
      RETURN
     END
*
      SUBROUTINE MONIT1(T,NPTS,NPDE,X,U,FMON)
*
      .. Scalar Arguments ..
     real
                        т
     INTEGER
                        NPDE, NPTS
      .. Array Arguments ..
*
     real
                        FMON(NPTS), U(NPDE,NPTS), X(NPTS)
      .. Local Scalars ..
     real
                        Н1, Н2, Н3
      INTEGER
                        Ι
      .. Intrinsic Functions ..
*
      INTRINSIC
                       ABS
      .. Executable Statements ..
*
     Executable Statements ..
     DO 20 I = 2, NPTS - 1
H1 = X(I) - X(I-1)
         H2 = X(I+1) - X(I)
```

```
H3 = 0.5e0 * (X(I+1) - X(I-1))
     Second derivatives ..
     FMON(I) = ABS(((U(1,I+1)-U(1,I))/H2-(U(1,I)-U(1,I-1))/H1)/H3)
20 CONTINUE
  FMON(1) = FMON(2)
  FMON(NPTS) = FMON(NPTS-1)
  RETURN
  END
  SUBROUTINE NMFLX1(NPDE,T,X,NCODE,V,ULEFT,URIGHT,FLUX,IRES)
   .. Scalar Arguments ..
  real
                     т, х
   INTEGER
                     IRES, NCODE, NPDE
   .. Array Arguments ..
  real
                     FLUX(NPDE), ULEFT(NPDE), URIGHT(NPDE), V(*)
   .. Executable Statements ..
```

```
FLUX(1) = ULEFT(1)
RETURN
END
```

9.1.2 Program Data

None.

*

*

*

*


*

9.1.3 Program Results

DO3PSF Example Program Results

Example 1

```
NPTS = 61 ATOL = 0.100E-03 RTOL = 0.100E-03
T = 0.100
           0.2000 0.3000
                          0.4000 0.5000 0.6000
                                                    0.7000
                                                            0.8000
Х
Approx U
           0.0000
                  0.1198
                          0.9461 0.1182
                                          0.0000
                                                    0.0000
                                                            0.0000
T = 0.200
           0.2000
                  0.3000 0.4000 0.5000
                                           0.6000
                                                    0.7000
                                                            0.8000
Х
Approx U
          0.0000
                  0.0007
                          0.1631 0.9015 0.1629
                                                   0.0001
                                                            0.0000
T = 0.300
           0.2000
                          0.4000 0.5000
                                                    0.7000
Х
                  0.3000
                                           0.6000
                                                            0.8000
          0.0000
                  0.0000
                          0.0025
                                  0.1924
                                          0.8596
                                                   0.1946
                                                            0.0002
Approx U
Number of integration steps in time =
                                      92
Number of function evaluations = 443
Number of Jacobian evaluations =
                                39
Number of iterations =
                       231
```



9.2 Example 2

This example is a linear advection equation with a non-linear source term and discontinuous initial profile:

$$\frac{\partial u}{\partial t} + \frac{\partial u}{\partial x} = -pu(u-1)(u-\frac{1}{2}),$$

for $0 \le x \le 1$ and $t \ge 0$. The discontinuity is modelled by a ramp function of width 0.01 and gradient 100, so that the exact solution at any time $t \ge 0$ is

$$u(x,t) = 1.0 + \max(\min(\delta, 0), -1),$$

where $\delta = 100(0.1 - x + t)$. The initial profile is given by the exact solution. The characteristic points into the domain at x = 0 and out of the domain at x = 1, and so a physical boundary condition u(0, t) = 1 is imposed at x = 0, with a numerical boundary condition at x = 1 which can be specified as u(1, t) = 0 since the discontinuity does not reach x = 1 during the time of integration.

The numerical flux is simply $\hat{F} = U_L$ at all times.

The remeshing monitor function (described below) is chosen to create an increasingly fine mesh towards the discontinuity in order to ensure good resolution of the discontinuity, but without loss of efficiency in the surrounding regions. However, refinement must be limited so that the time step required for stability does not become unrealistically small. The region of refinement must also keep up with the discontinuity as it moves across the domain, and hence it cannot be so small that the discontinuity moves out of the refined region between remeshing.

The above requirements mean that the use of the first or second spatial derivative of U for the monitor function is inappropriate; the large relative size of either derivative in the region of the discontinuity leads to extremely small mesh-spacing in a very limited region, and the solution is then far more expensive than for a very fine fixed mesh.

An alternative monitor function based on a cosine function proves very successful. It is only semiautomatic as it requires some knowledge of the solution (for problems without an exact solution an initial approximate solution can be obtained using a coarse fixed mesh). On each call to the user-supplied MONITF subroutine the discontinuity is located by finding the maximum spatial derivative of the solution. On the first call the desired width of the region of non-zero monitor function is set (this can be changed at a later time if desired). Then on each call the monitor function is assigned using a cosine function so that it has a value of one at the discontinuity down to zero at the edges of the predetermined region of refinement, and zero outside the region. Thus the monitor function and the subsequent refinement are limited, and the region is large enough to ensure that there is always sufficient refinement at the discontinuity.

9.2.1 Program Text

Note: the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
SUBROUTINE EX2
      .. Parameters ..
*
      INTEGER
                       NOUT
     PARAMETER
                       (NOUT=6)
     INTEGER
                       NPDE, NPTS, NCODE, NXI, NXFIX, NEQN, NIW, NWKRES,
                       LENODE, MLU, NW, INTPTS, ITYPE
     +
     PARAMETER
                        (NPDE=1,NPTS=61,NCODE=0,NXI=0,NXFIX=0,
                        NEQN=NPDE*NPTS+NCODE,NIW=25+NXFIX+NEQN,
     +
     +
                        NWKRES=NPDE*(2*NPTS+3*NPDE+32)+7*NPTS+3,
     +
                        LENODE=11*NEQN+50, MLU=3*NPDE-1, NW=(3*MLU+1)
                        *NEQN+NWKRES+LENODE, INTPTS=7, ITYPE=1)
      .. Local Scalars .
*
     real
                        CONST, DXMESH, TOUT, TRMESH, TS, XRATIO
                       I, IFAIL, IND, IPMINF, IT, ITASK, ITOL, ITRACE,
      INTEGER
                       M, NRMESH
     +
     LOGICAL
                       REMESH
      CHARACTER
                       LAOPT, NORM
      .. Local Arrays ..
*
     real
                       ALGOPT(30), ATOL(1), RTOL(1), U(NEQN),
     +
                        UE(1,INTPTS), UOUT(1,INTPTS,ITYPE), W(NW),
     +
                        X(NPTS), XFIX(1), XI(1), XOUT(INTPTS)
      INTEGER
                       IW(NIW)
      .. External Subroutines ..
*
     EXTERNAL BNDRY2, DO3PEK, DO3PSF, DO3PZF, EXACT, MONIT2,
+ NMFLX2, PDEF2, UVIN2
     +
        Data statements .
*
     DATA
                       XOUT(1)/0.0e+0/, XOUT(2)/0.3e+0/,
     +
                        XOUT(3)/0.4e+0/, XOUT(4)/0.5e+0/,
                        XOUT(5)/0.6e+0/, XOUT(6)/0.7e+0/, XOUT(7)/1.0e+0/
      .. Executable Statements ..
*
     WRITE (NOUT, *)
     WRITE (NOUT, *)
      WRITE (NOUT,*) 'Example 2'
      WRITE (NOUT, *)
*
      ITRACE = 0
      ITOL = 1
      NORM = '1'
     ATOL(1) = 0.5e-3
     RTOL(1) = 0.5e-1
     WRITE (NOUT, 99998) NPTS, ATOL, RTOL
*
      Initialise mesh ..
*
      DO 20 I = 1, NPTS
         X(I) = (I-1.0e0) / (NPTS-1.0e0)
  20 CONTINUE
     XFIX(1) = 0.0e0
*
      Set remesh parameters..
*
      REMESH = .TRUE.
     NRMESH = 5
      DXMESH = 0.0e^{0}
      CONST = 1.0e0/(NPTS-1.0e0)
      XRATIO = 1.5e0
      IPMINF = 0
     XI(1) = 0.0e0
      LAOPT = 'B'
```

```
IND = 0
      ITASK = 1
*
      DO 40 I = 1, 30
        ALGOPT(I) = 0.0e^{0}
   40 CONTINUE
      Theta integration ..
*
      ALGOPT(1) = 2.0e0
      ALGOPT(6) = 2.0e^{0}
      ALGOPT(7) = 2.0e0
      Max. time step ..
      ALGOPT(13) = 2.5e-3
      TS = 0.0e0
      TOUT = 0.0e0
      IFAIL = 0
      DO 80 IT = 1, 2
         TOUT = IT * 0.2e0
         CALL D03PSF(NPDE,TS,TOUT,PDEF2,NMFLX2,BNDRY2,UVIN2,U,NPTS,X,
                       NCODE, DO3PEK, NXI, XI, NEQN, RTOL, ATOL, ITOL, NORM, LAOPT,
     +
     +
                       ALGOPT, REMESH, NXFIX, XFIX, NRMESH, DXMESH, TRMESH,
     +
                       IPMINF, XRATIO, CONST, MONIT2, W, NW, IW, NIW, ITASK,
     +
                       ITRACE, IND, IFAIL)
*
         WRITE (NOUT, 99999) TS
         WRITE (NOUT, 99996)
         Interpolate at output points ..
*
         M = 0
         CALL D03PZF(NPDE,M,U,NPTS,X,XOUT,INTPTS,ITYPE,UOUT,IFAIL)
*
*
         Check against exact solution .
         CALL EXACT (TOUT, UE, XOUT, INTPTS)
         DO 60 I = 1, INTPTS
            WRITE (NOUT, 99995) XOUT(I), UOUT(1,I,1), UE(1,I)
   60
         CONTINUE
   80 CONTINUE
*
      WRITE (NOUT, 99997) IW(1), IW(2), IW(3), IW(5)
      RETURN
*
99999 FORMAT (' T = ', F6.3)
99998 FORMAT (/' NPTS = ',14,' ATOL = ',e10.3,' RTOL = ',e10.3,/)
99997 FORMAT (/' Number of integration steps in time = ',I6,/' Number ',
             'of function evaluations = ',I6,/' Number of Jacobian ',
'evaluations =',I6,/' Number of iterations = ',I6,/)
     +
99996 FORMAT (8X, 'X', 8X, 'Approx U', 4X, 'Exact U', /)
99995 FORMAT (3(3X,F9.4))
      END
*
      SUBROUTINE UVIN2(NPDE,NPTS,NXI,X,XI,U,NCODE,V)
      .. Scalar Arguments ..
*
                         NCODE, NPDE, NPTS, NXI
      TNTEGER
      .. Array Arguments ..
      real
                         U(NPDE,NPTS), V(*), X(NPTS), XI(*)
      .. Local Scalars ..
      real
                        Т
*
      .. External Subroutines ..
      EXTERNAL
                        EXACT
*
      .. Executable Statements ..
      T = 0.0e0
      CALL EXACT(T,U,X,NPTS)
      RETURN
      END
      SUBROUTINE PDEF2(NPDE,T,X,U,UX,NCODE,V,VDOT,P,C,D,S,IRES)
*
      .. Scalar Arguments ..
      real
                         т, х
      INTEGER
                         IRES, NCODE, NPDE
*
      .. Array Arguments ..
      real
                        C(NPDE), D(NPDE), P(NPDE,NPDE), S(NPDE), U(NPDE),
     +
                         UX(NPDE), V(*), VDOT(*)
```

```
.. Executable Statements ..
*
      P(1,1) = 1.0e0
      C(1) = 0.0e0
      D(1) = 0.0e0
      S(1) = -1.0e^{2} \times U(1) \times (U(1) - 1.0e^{0}) \times (U(1) - 0.5e^{0})
      RETURN
      END
*
      SUBROUTINE BNDRY2(NPDE,NPTS,T,X,U,NCODE,V,VDOT,IBND,G,IRES)
      .. Scalar Arguments ..
*
      real
                         Т
      INTEGER
                         IBND, IRES, NCODE, NPDE, NPTS
      .. Array Arguments ..
                         G(NPDE), U(NPDE, NPTS), V(*), VDOT(*), X(NPTS)
      real
      .. Local Arrays ..
*
      real
                         UE(1,1)
      .. External Subroutines ..
*
      EXTERNAL
                         EXACT
      .. Executable Statements ..
      Solution known to be constant at both boundaries ..
4
      IF (IBND.EQ.O) THEN
         CALL EXACT(T,UE,X(1),1)
         G(1) = UE(1,1) - U(1,1)
      ELSE
         CALL EXACT(T,UE,X(NPTS),1)
         G(1) = UE(1,1) - U(1,NPTS)
      END TF
      RETURN
      END
*
      SUBROUTINE NMFLX2(NPDE,T,X,NCODE,V,ULEFT,URIGHT,FLUX,IRES)
      .. Scalar Arguments ..
*
      real
                         т, Х
                         IRES, NCODE, NPDE
      INTEGER
      .. Array Arguments ..
      real
                         FLUX(NPDE), ULEFT(NPDE), URIGHT(NPDE), V(*)
      .. Executable Statements ..
      FLUX(1) = ULEFT(1)
      RETURN
      END
*
      SUBROUTINE MONIT2(T,NPTS,NPDE,X,U,FMON)
*
      .. Scalar Arguments ..
      real
                         Т
      INTEGER
                         NPDE, NPTS
      .. Array Arguments ..
      real
                         FMON(NPTS), U(NPDE,NPTS), X(NPTS)
      .. Local Scalars ..
*
                         H1, PI, UX, UXMAX, XL, XLEFT, XMAX, XR, XRIGHT,
      real
                         XA, XX
     +
      INTEGER
                         I, ICOUNT
      .. External Functions ..
*
      real
                         X01AAF
      EXTERNAL
                         X01AAF
      .. Intrinsic Functions .
      INTRINSIC
                        ABS, COS
*
      .. Data statements ..
                         XA/0.0e0/, ICOUNT/0/
      DATA
      .. Executable Statements ..
*
      XX = 0.0e0
      PI = XO1AAF(XX)
      Locate shock ..
      UXMAX = 0.0e0
      XMAX = 0.0e0
      DO 20 I = 2, NPTS - 1
         H1 = X(I) - X(I-1)
         UX = ABS((U(1,I)-U(1,I-1))/H1)
         IF (UX.GT.UXMAX) THEN
            UXMAX = UX
            XMAX = X(I)
         END IF
```

D03PSF

```
20 CONTINUE
      Assign width (on first call only) ..
*
      IF (ICOUNT.EQ.0) THEN
         ICOUNT = 1
         XLEFT = XMAX - X(1)
         XRIGHT = X(NPTS) - XMAX
         IF (XLEFT.GT.XRIGHT) THEN
            XA = XRIGHT
         ELSE
           XA = XLEFT
         END IF
     END IF
     XL = XMAX - XA
     XR = XMAX + XA
     Assign monitor function ..
*
     DO 40 I = 1, NPTS
         IF (X(I).GT.XL .AND. X(I).LT.XR) THEN
            FMON(I) = 1.0e0 + COS(PI \star (X(I) - XMAX) / XA)
         ELSE
            FMON(I) = 0.0e0
         END IF
   40 CONTINUE
     RETURN
     END
*
      SUBROUTINE EXACT(T,U,X,NPTS)
     Exact solution (for comparison and b.c. purposes)
*
*
      .. Scalar Arguments ..
     real
                       Т
      INTEGER
                       NPTS
*
      .. Array Arguments .
     real
                      U(1,NPTS), X(*)
      .. Local Scalars ..
     real
                       DEL, PSI, RM, RN, S
      INTEGER
                       Ι
      .. Executable Statements ..
*
      S = 0.1e0
     DEL = 0.01e0
     RM = -1.0e0/DEL
     RN = 1.0e0 + S/DEL
     DO 20 I = 1, NPTS
         PSI = X(I) - T
         IF (PSI.LT.S) THEN
            U(1,I) = 1.0e0
         ELSE IF (PSI.GT.(DEL+S)) THEN
           U(1,I) = 0.0e0
         ELSE
           U(1,I) = RM*PSI + RN
         END IF
   20 CONTINUE
     RETURN
     END
```

9.2.2 Program Data

None.

9.2.3 Program Results

```
DO3PSF Example Program Results

Example 2

NPTS = 61 ATOL = 0.500E-03 RTOL = 0.500E-01

T = 0.200

X Approx U Exact U
```

