# NAG Fortran Library Routine Document E04BBF/E04BBA

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

## 1 Purpose

E04BBF/E04BBA searches for a minimum, in a given finite interval, of a continuous function of a single variable, using function and first derivative values. The method (based on cubic interpolation) is intended for functions which have a continuous first derivative (although it will usually work if the derivative has occasional discontinuities).

E04BBA is a version of E04BBF that has additional parameters in order to make it safe for use in multithreaded applications (see Section 5 below).

# 2 Specifications

#### 2.1 Specification for E04BBF

```
SUBROUTINE E04BBF(FUNCT, E1, E2, A, B, MAXCAL, X, F, G, IFAIL)

INTEGER

MAXCAL, IFAIL

real

E1, E2, A, B, X, F, G

EXTERNAL

FUNCT
```

#### 2.2 Specification for E04BBA

```
SUBROUTINE E04BBA(FUNCT, E1, E2, A, B, MAXCAL, X, F, G, IUSER, RUSER,

IFAIL)

INTEGER

MAXCAL, IUSER(*), IFAIL

real

E1, E2, A, B, X, F, G, RUSER(*)

EXTERNAL

FUNCT
```

## 3 Description

E04BBF/E04BBA is applicable to problems of the form:

```
Minimize F(x) subject to a \le x \le b
```

when the first derivative  $\frac{dF}{dx}$  can be calculated. The routine normally computes a sequence of x values which tend in the limit to a minimum of F(x) subject to the given bounds. It also progressively reduces the interval [a,b] in which the minimum is known to lie. It uses the safeguarded cubic-interpolation method described in Gill and Murray (1973).

The user must supply a subroutine FUNCT to evaluate F(x) and  $\frac{dF}{dx}$ . The parameters E1 and E2 together specify the accuracy

$$Tol(x) = E1 \times |x| + E2$$

to which the position of the minimum is required. Note that FUNCT is never called at a point which is closer than Tol(x) to a previous point.

If the original interval [a,b] contains more than one minimum, E04BBF/E04BBA will normally find one of the minima.

[NP3546/20A] E04BBF/E04BBA.1

#### 4 References

Gill P E and Murray W (1973) Safeguarded steplength algorithms for optimization using descent methods NPL Report NAC 37 National Physical Laboratory

## 5 Parameters

1: FUNCT – SUBROUTINE, supplied by the user.

External Procedure

This routine must be supplied by the user to calculate the values of F(x) and  $\frac{dF}{dx}$  at any point x in [a,b].

It should be tested separately before being used in conjunction with E04BBF/E04BBA.

The specification of FUNCT for E04BBF is:

SUBROUTINE FUNCT(XC, FC, GC)

real XC, FC, GC

The specification of FUNCT for E04BBA is:

SUBROUTINE FUNCT(XC, FC, GC, IUSER, RUSER)

real XC, FC, GC, RUSER(\*)

1: XC – real Input

On entry: the point x at which the values of F and  $\frac{dF}{dx}$  are required.

2: FC – real Output

On exit: FC must be set to the value of the function F at the current point x.

3: GC – real Output

On exit: GC must be set to the value of the first derivative  $\frac{dF}{dx}$  at the current point x.

**Note:** the following are additional parameters for specific use of FUNCT with E04BBA. Users of E04BBF therefore need not read the remainder of this description.

4: IUSER(\*) – INTEGER array

User Workspace

5: RUSER(\*) – *real* array

User Workspace

FUNCT is called from E04BBA with the parameters IUSER and RUSER as supplied to E04BBA. You are free to use the arrays IUSER and RUSER to supply information to FUNCT.

FUNCT must be declared as EXTERNAL in the (sub)program from which E04BBF/E04BBA is called. Parameters denoted as *Input* must **not** be changed by this procedure.

2: E1 – real Input/Output

On entry: the relative accuracy to which the position of a minimum is required. (Note that, since E1 is a relative tolerance, the scaling of x is automatically taken into account.)

E1 should be no smaller than  $2\epsilon$ , and preferably not much less than  $\sqrt{\epsilon}$ , where  $\epsilon$  is the *machine precision*.

On exit: if the user sets E1 to 0.0 (or to any value less than  $\epsilon$ ), E1 will be reset to the default value  $\sqrt{\epsilon}$  before starting the minimization process.

E04BBF/E04BBA.2 [NP3546/20A]

3: E2 – **real** Input/Output

On entry: the absolute accuracy to which the position of a minimum is required. E2 should be no smaller than  $2\epsilon$ .

On exit: if the user sets E2 to 0.0 (or to any value less than  $\epsilon$ ), E2 will be reset to the default value  $\sqrt{\epsilon}$ .

4: A – real Input/Output

On entry: the lower bound a of the interval containing a minimum.

On exit: an improved lower bound on the position of the minimum.

5: B – real Input/Output

On entry: the upper bound b of the interval containing a minimum.

On exit: an improved upper bound on the position of the minimum.

#### 6: MAXCAL – INTEGER

Input/Output

On entry: the maximum number of calls of FUNCT to be allowed.

Constraint: MAXCAL  $\geq 2$ . (Few problems will require more than 20.)

There will be an error exit (see Section 6) after MAXCAL calls of FUNCT.

On exit: the total number of times that FUNCT was actually called.

7: X - real Output

On exit: the estimated position of the minimum.

8: F - real Output

On exit: the function value at the final point given in X.

9: G – real Output

On exit: the value of the first derivative at the final point in X.

10: IFAIL – INTEGER Input/Output

**Note:** for E04BBA, IFAIL does not occur in this position in the parameter list. See the additional parameters described below.

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, because for this routine the values of the output parameters may be useful even if IFAIL  $\neq 0$  on exit, the recommended value is -1. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

**Note:** the following are additional parameters for specific use with E04BBA. Users of E04BBF therefore need not read the remainder of this section.

# 10: IUSER(\*) – INTEGER array

User Workspace

**Note:** the dimension of the array IUSER must be at least 1.

IUSER is not used by E04BBA, but is passed directly to the external procedure FUNCT and may be used to pass information to that routine.

[NP3546/20A] E04BBF/E04BBA.3

11: RUSER(\*) - *real* array

User Workspace

Input/Output

Note: the dimension of the array RUSER must be at least 1.

RUSER is not used by E04BBA, but is passed directly to the external procedure FUNCT and may be used to pass information to that routine.

12: IFAIL – INTEGER

Note: see the parameter description for IFAIL above.

## 6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

On entry, 
$$(A + E2) \ge B$$
, or  $MAXCAL < 2$ .

IFAIL = 2

The number of calls of FUNCT has exceeded MAXCAL. This may have happened simply because MAXCAL was set too small for a particular problem, or may be due to a mistake in the user's routine FUNCT. If no mistake can be found in FUNCT, restart E04BBF/E04BBA (preferably with the values of A and B given on exit from the previous call of E04BBF/E04BBA).

# 7 Accuracy

If F(x) is  $\delta$ -unimodal for some  $\delta < Tol(x)$ , where  $Tol(x) = E1 \times |x| + E2$ , then, on exit, x approximates the minimum of F(x) in the original interval [a,b] with an error less than  $3 \times Tol(x)$ .

#### **8** Further Comments

Timing depends on the behaviour of F(x), the accuracy demanded and the length of the interval [a,b]. Unless F(x) and  $\frac{dF}{dx}$  can be evaluated very quickly, the run time will usually be dominated by the time spent in FUNCT.

If F(x) has more than one minimum in the original interval [a, b], E04BBF/E04BBA will determine an approximation x (and improved bounds a and b) for one of the minima.

If E04BBF/E04BBA finds an x such that  $F(x-\delta_1)>F(x)< F(x+\delta_2)$  for some  $\delta_1,\delta_2\geq Tol(x)$ , the interval  $[x-\delta_1,x+\delta_2]$  will be regarded as containing a minimum, even if F(x) is less than  $F(x-\delta_1)$  and  $F(x+\delta_2)$  only due to rounding errors in the user-supplied routine. Therefore FUNCT should be programmed to calculate F(x) as accurately as possible, so that E04BBF/E04BBA will not be liable to find a spurious minimum. (For similar reasons,  $\frac{dF}{dx}$  should be evaluated as accurately as possible.)

## 9 Example

A sketch of the function

$$F(x) = \frac{\sin x}{x}$$

shows that it has a minimum somewhere in the range [3.5, 5.0]. The following program shows how E04BBF/E04BBA can be used to obtain a good approximation to the position of a minimum.

E04BBF/E04BBA.4 [NP3546/20A]

### 9.1 Program Text

**Note:** the listing of the example program presented below uses **bold italicised** terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

**Note:** the following program illustrates the use of E04BBF. An equivalent program illustrating the use of E04BBA is available with the supplied Library and is also available from the NAG web site.

```
E04BBF Example Program Text.
*
      Mark 20 Revised.
*
      Mark 20 Revised. NAG Copyright 2001.
      .. Parameters ..
      TNTEGER
                       MOHT
      PARAMETER
                       (NOUT=6)
      .. Local Scalars ..
      real
                       A, B, EPS, F, G, T, X
                       IFAIL, MAXCAL
      INTEGER
      .. External Subroutines .
      EXTERNAL
                       EO4BBF, FUNCT
      .. Executable Statements ..
      WRITE (NOUT,*) 'E04BBF Example Program Results'
      EPS and T are set to zero so that EO4BBF will reset them to
      their default values
      EPS = 0.0e0
      T = 0.0e0
      The minimum is known to lie in the range (3.5, 5.0)
      A = 3.5e0
      B = 5.0e0
      Allow 30 calls of FUNCT
      MAXCAL = 30
      IFAIL = 1
      CALL EO4BBF(FUNCT, EPS, T, A, B, MAXCAL, X, F, G, IFAIL)
      WRITE (NOUT,*)
      IF (IFAIL.EQ.1) THEN
         WRITE (NOUT,*) 'Parameter outside expected range'
         IF (IFAIL.EQ.2) THEN
            WRITE (NOUT,*) 'Results after MAXCAL calls of FUNCT are'
            WRITE (NOUT,*)
         END IF
         WRITE (NOUT, 99999) 'The minimum lies in the interval ', A,
          ' to ', B
         WRITE (NOUT, 99999) 'Its estimated position is ', X, ','
         WRITE (NOUT,99998) 'where the function value is ^{\prime}, F
         WRITE (NOUT, 99997) 'and the gradient is ', G,
           ' (machine dependent)'
         WRITE (NOUT, 99996) MAXCAL, ' calls of FUNCT were required'
      END IF
      STOP
99999 FORMAT (1X,A,F10.8,A,F10.8)
99998 FORMAT (1X,A,F7.4)
99997 FORMAT (1X,A,1P,e8.1,A)
99996 FORMAT (1X, I2, A)
      END
      SUBROUTINE FUNCT(XC,FC,GC)
      Routine to evaluate F(x) and dF/dx at any point in (A, B)
      Routine to evaluate... Scalar Arguments .. FC, GC, XC
      real
      .. Intrinsic Functions ..
                       COS, SIN
      INTRINSIC
      .. Executable Statements ..
      FC = SIN(XC)/XC
      GC = (COS(XC) - FC)/XC
      RETURN
      END
```

[NP3546/20A] E04BBF/E04BBA.5

# 9.2 Program Data

None.

# 9.3 Program Results

E04BBF Example Program Results

The minimum lies in the interval 4.49340940 to 4.49340946 Its estimated position is 4.49340946, where the function value is -0.2172 and the gradient is 3.9E-16 (machine dependent) 6 calls of FUNCT were required