NAG Fortran Library Routine Document F04ATF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

1 Purpose

F04ATF calculates the accurate solution of a set of real linear equations with a single right-hand side, using an LU factorization with partial pivoting, and iterative refinement.

2 Specification

```
SUBROUTINE F04ATF(A, IA, B, N, C, AA, IAA, WKS1, WKS2, IFAIL)

INTEGER

IA, N, IAA, IFAIL

real

A(IA,*), B(*), C(*), AA(IAA,*), WKS1(*), WKS2(*)
```

3 Description

Given a set of real linear equations, Ax = b, the routine first computes an LU factorization of A with partial pivoting, PA = LU, where P is a permutation matrix, L is lower triangular and U is unit upper triangular. An approximation to x is found by forward and backward substitution in Ly = Pb and Ux = y. The residual vector r = b - Ax is then calculated using **additional precision**, and a correction d to x is found by solving LUd = r. x is replaced by x + d, and this iterative refinement of the solution is repeated until full machine accuracy is obtained.

4 References

Wilkinson J H and Reinsch C (1971) Handbook for Automatic Computation II, Linear Algebra Springer-Verlag

5 Parameters

1: A(IA,*) - real array Input

Note: the second dimension of the array A must be at least max(1, N).

On entry: the n by n matrix A.

2: IA – INTEGER Input

On entry: the first dimension of the array A as declared in the (sub)program from which F04ATF is called

Constraint: IA $\geq \max(1, N)$.

3: B(*) - real array Input

Note: the dimension of the array B must be at least max(1, N).

On entry: the right-hand side vector b.

4: N – INTEGER Input

On entry: n, the order of the matrix A.

Constraint: $N \ge 0$.

[NP3546/20A] F04ATF.1

5: C(*) - real array Output

Note: the dimension of the array C must be at least max(1, N).

On exit: the solution vector x.

6: AA(IAA,*) - real array

Output

Note: the second dimension of the array AA must be at least max(1, N).

On exit: the triangular factors L and U, except that the unit diagonal elements of U are not stored.

7: IAA – INTEGER Input

On entry: the first dimension of the array AA as declared in the (sub)program from which F04ATF is called.

Constraint: IAA $\geq \max(1, N)$.

8: WKS1(*) - real array

Workspace

Note: the dimension of the array WKS1 must be at least max(1, N).

9: WKS2(*) - real array

Workspace

Note: the dimension of the array WKS2 must be at least max(1, N).

10: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

The matrix A is singular, possibly due to rounding errors.

IFAIL = 2

Iterative refinement fails to improve the solution, i.e., the matrix A is too ill-conditioned.

IFAIL = 3

```
On entry, N < 0, or IA < max(1, N), or IAA < max(1, N).
```

7 Accuracy

The computed solutions should be correct to full machine accuracy. For a detailed error analysis see page 107 of Wilkinson and Reinsch (1971).

F04ATF.2 [NP3546/20A]

8 Further Comments

The time taken by the routine is approximately proportional to n^3 .

The routine must not be called with the same name for parameters B and C.

9 Example

To solve the set of linear equations Ax = b where

$$A = \begin{pmatrix} 33 & 16 & 72 \\ -24 & -10 & -57 \\ -8 & -4 & -17 \end{pmatrix} \quad \text{and} \quad b = \begin{pmatrix} -359 \\ 281 \\ 85 \end{pmatrix}.$$

9.1 Program Text

Note: the listing of the example program presented below uses **bold italicised** terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
FO4ATF Example Program Text
*
      Mark 15 Revised. NAG Copyright 1991.
      .. Parameters ..
      INTEGER
                       NMAX, IA, IAA
                       (NMAX=8,IA=NMAX,IAA=NMAX)
      PARAMETER
                       NIN, NOUT
      INTEGER
      PARAMETER
                       (NIN=5,NOUT=6)
      .. Local Scalars ..
      INTEGER
                       I, IFAIL, J, N
      .. Local Arrays ..
                       A(IA,NMAX), AA(IAA,NMAX), B(NMAX), C(NMAX),
      real
                       WKS1(NMAX), WKS2(NMAX)
      .. External Subroutines ..
                       F04ATF
      .. Executable Statements ..
      WRITE (NOUT,*) 'F04ATF Example Program Results'
      Skip heading in data Ûle
      READ (NIN, *)
      READ (NIN,*) N
      WRITE (NOUT, *)
      IF (N.GE.O .AND. N.LE.NMAX) THEN
         READ (NIN,*) ((A(I,J),J=1,N),I=1,N), (B(I),I=1,N)
         CALL FO4ATF(A, IA, B, N, C, AA, IAA, WKS1, WKS2, IFAIL)
         WRITE (NOUT, *) ' Solution'
         WRITE (NOUT, 99998) (C(I), I=1, N)
      ELSE
         WRITE (NOUT, 99999) 'N is out of range: N = ', N
      END IF
      STOP
99999 FORMAT (1X,A,I5)
99998 FORMAT (1X,F9.4)
      END
```

9.2 Program Data

```
F04ATF Example Program Data
3
33 16 72
-24 -10 -57
-8 -4 -17
-359 281 85
```

[NP3546/20A] F04ATF.3

9.3 Program Results

FO4ATF Example Program Results

Solution

- 1.0000
- -2.0000 -5.0000

F04ATF.4 (last) [NP3546/20A]