X03 – Inner Products X03ABF

# NAG Fortran Library Routine Document

# X03ABF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

# 1 Purpose

X03ABF calculates the value of a *complex* scalar product using *basic precision* or *additional precision* and adds it to a *complex* initial value.

# 2 Specification

```
SUBROUTINE XO3ABF(A, ISIZEA, B, ISIZEB, N, ISTEPA, ISTEPB, CX, DX, SW,

IFAIL)

INTEGER

ISIZEA, ISIZEB, N, ISTEPA, ISTEPB, IFAIL

complex

A(ISIZEA), A(ISIZEA), B(ISIZEB), CX, DX

LOGICAL

SW
```

# 3 Description

The routine calculates the scalar product of two *complex* vectors and adds it to an initial value c to give a correctly rounded result d:

$$d = c + \sum_{i=1}^{n} a_i b_i.$$

If n < 1, d = c.

The vector elements  $a_i$  and  $b_i$  are stored in selected elements of the one-dimensional array parameters A and B, which in the (sub)program from which X03ABF is called may be identified with parts of possibly multi-dimensional arrays according to the standard Fortran rules. For example, the vectors may be parts of a row or column of a matrix. See Section 5 for details, and Section 9 for an example.

The products are accumulated in basic precision or additional precision depending on the parameter SW.

This routine has been designed primarily for use as an auxiliary routine by other routines in the NAG Fortran Library, especially those in the chapters on Linear Algebra.

# 4 References

None.

#### 5 Parameters

1: A(ISIZEA) – *complex* array

Input

On entry: the elements of the first vector.

The *i*th vector element is stored in the array element  $A((i-1) \times ISTEPA + 1)$ . In the user's (sub)program from which X03ABF is called, A can be part of a multi-dimensional array and the actual argument must be the array element containing the first vector element.

[NP3546/20A] X03ABF.1

#### 2: ISIZEA – INTEGER

Input

On entry: the dimension of array A inside the routine.

The upper bound for ISIZEA is found by multiplying together the dimensions of A as declared in the (sub)program from which X03ABF is called, subtracting the starting position and adding 1.

*Constraint*: ISIZEA  $\geq$  (N - 1)  $\times$  ISTEPA + 1.

#### 3: B(ISIZEB) – *complex* array

Input

On entry: the elements of the second vector.

The *i*th vector element is stored in the array element  $B((i-1) \times ISTEPB + 1)$ . In the (sub)program from which X03ABF is called, B can be part of a multi-dimensional array and the actual argument must be the array element containing the first vector element.

#### 4: ISIZEB – INTEGER

Input

On entry: the dimension of array B inside the routine.

The upper bound for ISIZEB is found by multiplying together the dimensions of B as declared in the user's (sub)program from which X03ABF is called, subtracting the starting position and adding 1.

Constraint: ISIZEB  $\geq (N-1) \times ISTEPB + 1$ .

#### 5: N – INTEGER

Input

On entry: the number of elements in the scalar product, n.

#### 6: ISTEPA – INTEGER

Input

On entry: the step length between elements of the first vector in array A.

Constraint: ISTEPA > 0.

#### 7: ISTEPB – INTEGER

Input

On entry: the step length between elements of the second vector in array B.

Constraint: ISTEPB > 0.

#### 8: CX - complex

Input

On entry: the initial value c.

#### 9: DX - complex

Output

On exit: the result d.

#### 10: SW – LOGICAL

Input

On entry: the precision to be used.

If SW = .TRUE., additional precision.

If SW = .FALSE., basic precision.

#### 11: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the

X03ABF.2 [NP3546/20A]

X03 – Inner Products X03ABF

value 1 is recommended. Otherwise, for users not familiar with this parameter the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

# 6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

```
\begin{split} \text{IFAIL} &= 1 \\ &\quad \text{On entry, ISTEPA} \leq 0, \\ &\quad \text{or} \quad \text{ISTEPB} \leq 0. \end{split} \begin{aligned} \text{IFAIL} &= 2 \\ &\quad \text{On entry, ISIZEA} < (N-1) \times \text{ISTEPA} + 1, \\ &\quad \text{or} \quad \text{ISIZEB} < (N-1) \times \text{ISTEPB} + 1. \end{aligned}
```

## 7 Accuracy

If the calculation is in *additional precision*, the result is correct to full implementation accuracy provided that exceptionally severe cancellation does not occur in the summation. If the calculation is in *basic precision*, such accuracy cannot be guaranteed.

#### **8** Further Comments

The time taken by the routine is approximately proportional to n and also depends on whether **basic precision** or **additional precision** is used.

#### 9 Example

To calculate the scalar product of the second column of the matrix A and the vector B, and add it to an initial value of 1+i, where

$$A = \begin{pmatrix} -1 & -i & 1 \\ 2+3i & i & 2i \\ 0 & -1-i & 1-2i \end{pmatrix}, \quad B = \begin{pmatrix} i \\ 1-i \\ -i \end{pmatrix}.$$

### 9.1 Program Text

**Note:** the listing of the example program presented below uses *bold italicised* terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
XO3ABF Example Program Text
Mark 14 Revised. NAG Copyright 1989.
.. Parameters ..
                 N
INTEGER
PARAMETER
                 (N=3)
INTEGER
                 NIN, NOUT
PARAMETER
                 (NIN=5,NOUT=6)
.. Local Scalars ..
complex
                 CX, DX
INTEGER
                 I, IFAIL, ISIZEA, ISIZEB, ISTEPA, ISTEPB, J
LOGICAL
.. Local Arrays ..
complex
                 A(N,N), B(N)
.. External Subroutines ..
EXTERNAL
                 X03ABF
.. Executable Statements ..
WRITE (NOUT, *) 'X03ABF Example Program Results'
Skip heading in data file
```

[NP3546/20A] X03ABF.3

```
READ (NIN,*)
READ (NIN,*)
(READ (NIN,*) ((A(I,J),J=1,N),I=1,N), (B(I),I=1,N)
CX = (1.0e0,1.0e0)
ISIZEA = N
ISIZEB = N
ISTEPA = 1
ISTEPB = 1
SW = .TRUE.
IFAIL = 0

*
CALL XO3ABF(A(1,2),ISIZEA,B,ISIZEB,N,ISTEPA,ISTEPB,CX,DX,SW,IFAIL)
*
WRITE (NOUT,*)
WRITE (NOUT,*)
WRITE (NOUT,99999) 'Result = ', DX
STOP
*
99999 FORMAT (1X,A,'(',F3.0,',',F3.0,')')
END
```

## 9.2 Program Data

### 9.3 Program Results

```
X03ABF Example Program Results
Result = ( 2., 3.)
```

X03ABF.4 (last) [NP3546/20A]