

Real-Time Workshop[®] Release Notes

How to Contact The MathWorks



www.mathworks.com Web
comp.soft-sys.matlab Newsgroup
www.mathworks.com/contact_TS.html Technical Support



suggest@mathworks.com Product enhancement suggestions
bugs@mathworks.com Bug reports
doc@mathworks.com Documentation error reports
service@mathworks.com Order status, license renewals, passcodes
info@mathworks.com Sales, pricing, and general information



508-647-7000 (Phone)



508-647-7001 (Fax)



The MathWorks, Inc.
3 Apple Hill Drive
Natick, MA 01760-2098

For contact information about worldwide offices, see the MathWorks Web site.

Real-Time Workshop® *Release Notes*

© COPYRIGHT 2000–2009 by The MathWorks, Inc.

The software described in this document is furnished under a license agreement. The software may be used or copied only under the terms of the license agreement. No part of this manual may be photocopied or reproduced in any form without prior written consent from The MathWorks, Inc.

FEDERAL ACQUISITION: This provision applies to all acquisitions of the Program and Documentation by, for, or through the federal government of the United States. By accepting delivery of the Program or Documentation, the government hereby agrees that this software or documentation qualifies as commercial computer software or commercial computer software documentation as such terms are used or defined in FAR 12.212, DFARS Part 227.72, and DFARS 252.227-7014. Accordingly, the terms and conditions of this Agreement and only those rights specified in this Agreement, shall pertain to and govern the use, modification, reproduction, release, performance, display, and disclosure of the Program and Documentation by the federal government (or other entity acquiring for or through the federal government) and shall supersede any conflicting contractual terms or conditions. If this License fails to meet the government's needs or is inconsistent in any respect with federal procurement law, the government agrees to return the Program and Documentation, unused, to The MathWorks, Inc.

Trademarks

MATLAB and Simulink are registered trademarks of The MathWorks, Inc. See www.mathworks.com/trademarks for a list of additional trademarks. Other product or brand names may be trademarks or registered trademarks of their respective holders.

Patents

The MathWorks products are protected by one or more U.S. patents. Please see www.mathworks.com/patents for more information.

Summary by Version	1
Version 7.3 (R2009a) Real-Time Workshop Software ..	5
Version 7.2 (R2008b) Real-Time Workshop Software ..	12
Version 7.1.1 (R2008a+) Real-Time Workshop Software	21
Version 7.1 (R2008a) Real-Time Workshop Software ..	22
Version 7.0.1 (R2007b+) Real-Time Workshop Software	30
Version 7.0 (R2007b) Real-Time Workshop Software ..	31
Version 6.6.1 (R2007a+) Real-Time Workshop Software	44
Version 6.6 (R2007a) Real-Time Workshop Software ..	45
Version 6.5 (R2006b) Real-Time Workshop Software ..	53
Version 6.4.1 (R2006a+) Real-Time Workshop Software	61
Version 6.4 (R2006a) Real-Time Workshop Software ..	62
Version 6.3 (R14SP3) Real-Time Workshop Software ..	74
Version 6.2.1 (R14SP2+) Real-Time Workshop Software	81

Version 6.2 (R14SP2) Real-Time Workshop Software ..	82
Version 6.1 (R14SP1) Real-Time Workshop Software ..	92
Version 6.0 (R14) Real-Time Workshop Software	93
Version 5.2 (R13SP2) Real-Time Workshop Software ..	144
Version 5.1.1 (R13SP1+) Real-Time Workshop Software	145
Version 5.1 (R13SP1) Real-Time Workshop Software ..	147
Version 5.0.1 (R13+) Real-Time Workshop Software ...	148
Version 5.0 (R13) Real-Time Workshop Software	151
Version 4.1 (R12.1) Real-Time Workshop Software	182
Version 4.0 (R12) Real-Time Workshop Software	196
Compatibility Summary for Real-Time Workshop Software	212

Summary by Version

This table provides quick access to what's new in each version. For clarification, see "Using Release Notes" on page 2.

Version (Release)	New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Latest Version V7.3 (R2009a)	Yes Details	Yes Summary	Bug Reports Includes fixes	Printable Release Notes: PDF Current product documentation
V7.2 (R2008b)	Yes Details	Yes Summary	Bug Reports Includes fixes	No
V7.1.1 (R2008a+)	No	No	Bug Reports Includes fixes	No
V7.1 (R2008a)	Yes Details	Yes Summary	Bug Reports Includes fixes	No
V7.0.1 (R2007b+)	No	No	Bug Reports Includes fixes	No
V7.0 (R2007b)	Yes Details	Yes Summary	Bug Reports Includes fixes	No
V6.6.1 (R2007a+)	No	No	Bug Reports Includes fixes	No
V6.6 (R2007a)	Yes Details	Yes Summary	Bug Reports Includes fixes	No
V6.5 (R2006b)	Yes Details	Yes Summary	Bug Reports Includes fixes	No
V6.4.1 (R2006a+)	No	No	Bug Reports Includes fixes	No
V6.4 (R2006a)	Yes Details	Yes Summary	Bug Reports Includes fixes	No

Version (Release)	New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
V6.3 (R14SP3)	Yes Details	Yes Summary	Bug Reports Includes fixes	No
V6.2.1 (R14SP2+)	No	No	Bug Reports Includes fixes	No
V6.2 (R14SP2)	Yes Details	No	Bug Reports Includes fixes	No
V6.1 (R14SP1)	Yes Details	No	Fixed bugs	No
V6.0 (R14)	Yes Details	Yes Summary	Fixed bugs	No
V5.2 (R13SP2)	No	No	Fixed bugs	V5.2 product documentation
V5.1.1 (R13SP1+)	Yes Details	Yes Summary	Fixed bugs	No
V5.1 (R13SP1)	No	No	Fixed bugs	No
V5.0.1 (R13+)	Yes Details	No	Fixed bugs	No
V5.0 (R13)	Yes Details	Yes Summary	Fixed bugs	No
V4.1 (R12.1)	Yes Details	Yes Summary	Fixed bugs	No
V4.0 (R12)	Yes Details	Yes Summary	No bug fixes	No

Using Release Notes

Use release notes when upgrading to a newer version to learn about:

- New features

- Changes
- Potential impact on your existing files and practices

Review the release notes for other MathWorks™ products required for this product (for example, MATLAB® or Simulink®) for enhancements, bugs, and compatibility considerations that also might impact you.

If you are upgrading from a software version other than the most recent one, review the release notes for all interim versions, not just for the version you are installing. For example, when upgrading from V1.0 to V1.2, review the release notes for V1.1 and V1.2.

What's in the Release Notes

New Features and Changes

- New functionality
- Changes to existing functionality

Version Compatibility Considerations

When a new feature or change introduces a reported incompatibility between versions, the **Compatibility Considerations** subsection explains the impact.

Compatibility issues reported after the product is released appear under Bug Reports at The MathWorks™ Web site. Bug fixes can sometimes result in incompatibilities, so you should also review the fixed bugs in Bug Reports for any compatibility impact.

Fixed Bugs and Known Problems

The MathWorks offers a user-searchable Bug Reports database so you can view Bug Reports. The development team updates this database at release time and as more information becomes available. This includes provisions for any known workarounds or file replacements. Information is available for bugs existing in or fixed in Release 14SP2 or later. Information is not available for all bugs in earlier releases.

Access Bug Reports using your MathWorks Account.

Version 7.3 (R2009a) Real-Time Workshop Software

This table summarizes what's new in V7.3 (R2009a):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	Bug Reports Includes fixes	Printable Release Notes: PDF Current product documentation

- “Parallel Builds Accelerate Code Generation and Compilation for Large Model Reference Hierarchies” on page 5
- “External Mode Simulation Now Supports Parameter and Signal Values with Data Types Larger Than 32 Bits” on page 6
- “Ability to Multiplex Compatible Asynchronous Function Calls” on page 6
- “Ability to Control Safe Cast Code Generated for Enumerated Types” on page 7
- “Open Watcom C/C++ Compiler Support for Model Reference Builds” on page 7
- “New Compilation Report for emlc” on page 7
- “emlc Support for Emulation Code Generation Target” on page 8
- “Changes to the Signal Properties Dialog Box” on page 8
- “New Reference Pages” on page 10
- “New Real-Time Workshop Reserved Keywords” on page 11
- “New and Enhanced Demos” on page 11

Parallel Builds Accelerate Code Generation and Compilation for Large Model Reference Hierarchies

R2009a provides the ability to accelerate code generation and compilation for models containing large model reference hierarchies by building referenced

models in parallel whenever possible. For example, you can distribute code generation and compilation for each model block across the cores of a multicore host computer. For more information, see “Reducing Build Time for Referenced Models” in the Real-Time Workshop® User’s Guide.

For information on how to configure a custom embedded target to support parallel builds, see “Supporting Model Referencing” in the Real-Time Workshop® Embedded Coder™ Developing Embedded Targets documentation.

External Mode Simulation Now Supports Parameter and Signal Values with Data Types Larger Than 32 Bits

External mode simulation now supports the ability to upload and download parameter values and upload signal values with data types larger than 32 bits, including

- Multiword data types, such as a 128-bit fixed-point integer on a 32-bit system
- 64-bit long on a 64-bit system

External mode simulation seamlessly supports interaction between host and target platforms with different native sizes and different endianness. For example, you can upload a 64-bit quantity from a 64-bit target system, using a 64-bit long, to a 32-bit host system, using a multiword comprised of two 32-bit integers.

Before this release, Simulink normal mode simulation and Real-Time Workshop code generation supported fixed-point data types larger than 32 bits, but external mode simulation did not.

Ability to Multiplex Compatible Asynchronous Function Calls

R2009a provides the ability to more flexibly multiplex asynchronous function calls, provided they have equal priority and use the base rate timer. This enhancement allows you to model asynchronous events that need to share algorithmic code in a natural way, without resorting to workarounds such as inserting blocks that do not intuitively contribute to your design.

Before this change, the Real-Time Workshop software supported the ability to multiplex compatible asynchronous function calls for sharing algorithmic code, but required that each caller was at the top level of its task. That is, each asynchronous function call had to connect directly to the Mux block, with no intervening calls to other blocks.

R2009a removes the requirement that each caller must be at the top level of an asynchronous task, so that you can freely multiplex any combination of direct and cascaded asynchronous function calls of equal priority that use the base rate timer.

Ability to Control Safe Cast Code Generated for Enumerated Types

In previous releases, code generated for a Simulink Data Type Conversion block always used a safe cast function when casting data to an enumerated type. In R2009a, such code uses safe casting only if the block's **Saturate on integer overflow** option is selected. See “Enumerated Type Safe Casting” for more information.

Open Watcom C/C++ Compiler Support for Model Reference Builds

The Real-Time Workshop software now supports use of the Open Watcom C/C++ compiler for builds of models with model reference hierarchies on 32-bit Windows platforms. Previously, model reference builds were not supported.

New Compilation Report for emlc

The new compilation report provides compile-time type information for the variables and expressions in your M-code. This information simplifies finding sources of error messages and aids understanding of type propagation rules. For more information, see “Working with Compilation Reports” in the Real-Time Workshop User's Guide.

Compatibility Considerations

The following internal and external browsers do not support the new compilation report:

- MATLAB internal browser (on 64-bit UNIX® platforms only)
- MACI internal browser
- Microsoft Internet Explorer® 6


To view the compilation report, you must have your MATLAB Web preferences configured to use an external browser, for example, Mozilla Firefox. To learn how to configure your MATLAB Web preferences, see “Specifying the System Browser MATLAB Uses for UNIX Platforms” in the MATLAB documentation.

emlc Support for Emulation Code Generation Target


emlc now supports both production and emulation code generation targets. For more information, see “Hardware Implementation Dialog Box for Embedded MATLAB™ Coder” in the Real-Time Workshop Reference.

Changes to the Signal Properties Dialog Box

The appearance of the **Real-Time Workshop** tab of the Signal Properties dialog box has changed in R2009a. The **Real-Time Workshop** tab previously looked like this by default:




In R2009a, the tab looks like this by default:



The changes between R2008b and R2009a are:

- A new property, **Package**, exists at the top of the top of the tab. When the value of **Package** is --- None ---, the rest of the tab behaves as it did in R2008b.
- The **RTW storage class** property has been renamed **Storage class**. It is functionally unchanged and has the same API as in R2008b.
- The **RTW storage type qualifier** property has been renamed **Storage type qualifier**. It is functionally unchanged and has the same API, but its GUI behavior is different:
 - **RTW storage type qualifier** was always visible, but was active only when it was applicable.
 - **Storage type qualifier** is visible only when it is applicable, and is hidden otherwise.

The next figure shows the **Storage type qualifier** property, which is visible because it is applicable when the **Storage class** is ImportedExternPointer.



For information about using **Storage class** and **Storage type qualifier** with GRT targets, see “Signal Storage, Optimization, and Interfacing” and “Simulink Data Objects and Code Generation”.

For information about using **Package**, **Storage class**, and **Storage type qualifier** with ERT targets, see “Applying CSCs to Parameters and Signals” in the Real-Time Workshop Embedded Coder documentation.

New Reference Pages

Existing Real-Time Workshop functions shown in the following table, are now documented in reference pages.

Function	Description
rtwbuild	Initiate the build process
rtwrebuild	Rebuild generated code
tlc	Invoke the Target Language Compiler

New Real-Time Workshop Reserved Keywords

Matrix and vector are now on the Real-Time Workshop Language Keywords list. For more information, see “Reserved Keywords”.

New and Enhanced Demos

Beginning with R2009a, the Real-Time Workshop Demos page uses a new format to display Real-Time Workshop and Real-Time Workshop Embedded Coder demos. The differences include:

- Indentation now is used to designate a functionally-related group of demos. Indentation no longer identifies demos for which the Real-Time Workshop Embedded Coder software is required.
- If a demo requires Real-Time Workshop Embedded Coder software, the demo naming or text identifies the requirement.

The following demo has been added in R2009a:

Demo...	Shows How You Can...
rtwdemo_usingrtw	Quickly generate C code for real-time simulation, rapid prototyping, or hardware-in-the-loop (HIL) testing applications. You select a Real-Time Workshop target for a model, generate code, and view the resulting files.

Version 7.2 (R2008b) Real-Time Workshop Software

This table summarizes what's new in V7.2 (R2008b):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	Bug Reports Includes fixes	No

New features and changes introduced in this version are

- “Support for Enumerated Data Types in Generated C Code” on page 13
- “Support for Simulink Legacy Code Tool Enhancement” on page 13
- “emlc Support for Fixed-Point Data Types Greater Than 32 Bits (Up to 128 Bits)” on page 14
- “File Structure of C Code Generated by emlc Now Matches M-File Structure” on page 14
- “emlc Uses Same Trigonometric Functions as MATLAB” on page 15
- “Improperly-Scaled Fixed-Point Relational Operators Now Match MATLAB Results” on page 15
- “emlc Now Prevents Default fimath Mismatches for MEX Functions” on page 15
- “Ability to Optimize Code for Vector Assignments by Replacing for-Loops with memcpy” on page 15
- “Rate Transition Support Enhanced for Signal Line Branching and Direct Connections Between Asynchronous Rates” on page 16
- “Generated Code Includes Standard C Static Files (stddef.h and stdlib.h) Only When Necessary” on page 17
- “MISRA C Code Initialization Enhancements” on page 17

- “Ability to Register Keywords to Avoid Conflicts with External Code” on page 18
- “Use Same Custom Code Settings for Model Simulation and Real-Time Workshop Code Generation” on page 18
- “Configure Unique Custom Code Settings for Library Models in the Configuration Parameters Dialog Box” on page 19
- “Flexible Configuration Options for Referenced Models in TLC-Based Custom Targets” on page 19
- “Optimize Floating-Point to Integer Data Type Conversions Using New Configuration Parameter” on page 20
- “New and Enhanced Demos” on page 20

Support for Enumerated Data Types in Generated C Code

Real-Time Workshop software now supports enumerated data types in code generated for Simulink models and Stateflow® charts. For details, see:

- “Using Enumerated Data” in the Simulink documentation
- “Using Enumerated Data in Stateflow Charts”
- “Enumerated Data Types in Generated Code”

Support for Simulink Legacy Code Tool Enhancement

The Real-Time Workshop software supports the new Legacy Code Tool S-function options field, `singleCPPMexFile`. When set (1), this option

- Requires you to generate and manage an inlined S-function as only one file (.cpp) instead of two (.c and .tlc)
- Maintains model code style — level of parentheses usage and preservation of operand order in expressions and condition expressions in `if` statements—as specified by model configuration parameters

When you choose not to use this option, code generated by the Legacy Code Tool does not reflect code style configuration settings and requires you to manage C MEX and TLC files.

For more information, see

- “Integrating Existing C Functions into Simulink Models with the Legacy Code Tool” in the Writing S-Functions documentation
- “Automating the Generation of Files for Fully Inlined S-Functions Using Legacy Code Tool” in the Real-Time Workshop documentation
- `legacy_code` function reference page

Compatibility Considerations

- If you upgrade from an earlier release, you can continue to use S-functions generated from the Legacy Code Tool available in earlier releases. You can continue to compile the S-function source code and you can continue to use the compiled output from an earlier release without recompiling the code.
- If you set the new `singleCPPMexFile` options field to true (1) when creating an S-function, you cannot use that S-function, in source or compiled form, with versions of Simulink earlier than Version 7.2 (R2008b).

emlc Support for Fixed-Point Data Types Greater Than 32 Bits (Up to 128 Bits)

`emlc` now supports fixed-point word lengths up to 128 bits for C code production. This increase in maximum precision to 128 bits supports generating efficient code for targets with nonstandard word sizes.

File Structure of C Code Generated by emlc Now Matches M-File Structure

In previous releases `emlc` generated code in a single C file, no matter how many source M files were compiled. Now, the generated C file structure matches the original M-file structure. `emlc` generates one C file for every M file for which a separate top-level function is generated. This association makes it easier to correlate the generated C code with the compiled M-code. For more information, see “Partitioning Generated Files for Readability” in the Real-Time Workshop documentation.

emlc Uses Same Trigonometric Functions as MATLAB

emlc now uses the same library as MATLAB for implementing trigonometric operations in MEX function targets. In previous releases, emlc used the C compiler implementation of trigonometric functions, sometimes producing different results from MATLAB. Now, results are consistent with MATLAB and independent of compiler choice.

Improperly-Scaled Fixed-Point Relational Operators Now Match MATLAB Results

When evaluating relational operators, emlc computes a common type that encompasses both input operands. In previous releases, if the common type required more than 32 bits, code generated by emlc may have given different answers from MATLAB. Now, the answers are consistent.

Compatibility Consideration

Some relational operators generate multi-word code even if one of the fixed-point operands is not a multi-word value. To work around this issue, cast both operands to the same fixed-point type (using the same scaling method and properties).


emlc Now Prevents Default fimath Mismatches for MEX Functions

MEX functions generated with emlc use the default fimath value in effect at compile time. If you do not specify a default fimath value explicitly using the -F option, emlc uses the MATLAB default fimath value. If your MEX function uses the MATLAB default fimath, emlcmex generates an error if the compile-time value does not match the runtime value.

Ability to Optimize Code for Vector Assignments by Replacing for-Loops with memcpy

This release provides two new model parameters, **Use memcpy for vector assignment** and **Memcpy threshold (bytes)**, which allow you to optimize Real-Time Workshop generated code for vector assignments by replacing for-loops with memcpy function calls. The new parameters appear on the

Optimization pane of the Configuration Parameters dialog box, immediately under the **Loop unrolling threshold** parameter.



Loop unrolling threshold: 5

Use memcopy for vector assignment Memcopy threshold (bytes): 64

The memcopy function can be more efficient than for-loop controlled element assignment for large data sets. Where memcopy offers improved execution speed, you can use the new model options to specify that generated code should use memcopy when assigning a vector signal.

Selecting the **Use memcopy for vector assignment** option enables the associated parameter **Memcopy threshold (bytes)**, which allows you to specify the array size in bytes at or above which memcopy should replace for-loops in the generated code for vector assignments. For more information, see “Use memcopy for vector assignment” and “Memcopy threshold (bytes)” in the *Simulink Graphical User Interface* documentation.

Rate Transition Support Enhanced for Signal Line Branching and Direct Connections Between Asynchronous Rates

Branching Supported on Output Port of Asynchronous Rate Transition Block

In previous releases, if a signal branched in order to drive multiple asynchronous subsystems, each branch of the signal required a separate Rate Transition block. In this release, you can place a single Rate Transition block on the signal line ahead of the branch, and then branch on the Rate Transition block output signal line. Eliminating the need for multiple Rate Transition blocks simplifies the model diagram and can improve code efficiency.

Asynchronous Subsystems Can Directly Connect When Rate Transition Protection Not Required

In previous releases, Rate Transition blocks were required at each port of an asynchronous subsystem, even when rate transition protection was not

required. Generally, rate transition protection is not required when the sample times for a signal's source and destination blocks have the same priority.

In this release, Rate Transition blocks can be omitted where rate transition protection is unnecessary, allowing direct connection between asynchronous subsystems. Specifically,

- Two asynchronous function-call subsystems with the same priority now can be directly connected
- An asynchronous function-call subsystem can have a direct feedback loop with no Rate Transition block in the loop

Eliminating Rate Transition blocks where rate transition protection is not required simplifies the model diagram and can improve code efficiency.

Generated Code Includes Standard C Static Files (stddef.h and stdlib.h) Only When Necessary

In previous releases, code generated by the Real-Time Workshop software always included the `stddef.h` header file, and for Stateflow content, the `stdlib.h` header file, regardless of the specific needs of the application or the target environment. In this release, generated code does not automatically include `stddef.h` or `stdlib.h` unless your model contains a utility function that requires it.

MISRA C Code Initialization Enhancements

Previously, the Real-Time Workshop build process occasionally generated initialization code that was not compliant with MISRA C® standards. In R2008b, using the **Use memset to initialize floats and doubles to 0.0** optimization generates initialization code that is always MISRA C compliant, resulting in safer, more efficient code. For details, see “Use memset to initialize floats and doubles to 0.0” in the Simulink documentation.

Compatibility Considerations

- For models you created previously that have the **Use memset to initialize floats and doubles to 0.0** check box cleared, if you rebuild using R2008b

Real-Time Workshop software, the generated code size might increase. To generate smaller code, select the **Use memset to initialize floats and doubles to 0.0** check box. The “Check optimization settings” Model Advisor check is available to help you determine if the current setting of the parameter is correct.

- If your hardware does not represent numerical zero for floating-point data as bit pattern 0 (all bits 0), you must clear the **Use memset to initialize floats and doubles to 0.0** check box.
- The **Use memset to initialize floats and doubles to 0.0** check box is selected by default for new models.

Ability to Register Keywords to Avoid Conflicts with External Code

Previously, external environments could use keywords that the Real-Time Workshop code generation process created in the generated code, resulting in clashes between the external environment and the generated code. In R2008b, you can register the set of keywords that the code generation process should not use, facilitating code integration where outside functions and global variables are unknown in the Simulink model.

The **Reserved names** parameter is located on the **Real-Time Workshop > Symbols** pane in the Configuration Parameters dialog box. For more information, see “Real-Time Workshop Pane: Symbols” in the Real-Time Workshop Reference and “Configuring Real-Time Workshop Code Generation Parameters” in the Real-Time Workshop User’s Guide.

Use Same Custom Code Settings for Model Simulation and Real-Time Workshop Code Generation

Previously, for models that contained Embedded MATLAB Function blocks, Stateflow charts, or Truth Table blocks, custom code settings for simulation and Real-Time Workshop code generation were entered separately. In R2008b, you can choose to use the same custom code settings in both cases to avoid entering information twice.

The **Use the same custom code settings as Simulation Target** parameter is located on the **Real-Time Workshop > Custom Code** pane in the Configuration Parameters dialog box. For more information, see “Real-Time

Workshop Pane: Custom Code” in the Real-Time Workshop Reference and “Configuring Real-Time Workshop Code Generation Parameters” in the Real-Time Workshop User’s Guide.

Configure Unique Custom Code Settings for Library Models in the Configuration Parameters Dialog Box

In general, library models use custom code settings of the parent model during the Real-Time Workshop build process. However, libraries that contain Embedded MATLAB Function blocks, Stateflow charts, or Truth Table blocks can use custom code settings unique from the parent model. These libraries can have their own set of Real-Time Workshop configuration parameters separate from the parameters of the parent model. Select **Tools > Open RTW Target** in the Embedded MATLAB Editor or Stateflow Editor for your library model.

For information about custom code parameters, see “Real-Time Workshop Pane: Custom Code” in the Real-Time Workshop Reference and “Configuring Real-Time Workshop Code Generation Parameters” in the Real-Time Workshop User’s Guide.

Compatibility Considerations

Previously, you could configure custom code for a Stateflow library model on the **Custom Code** pane in the RTW Target dialog box. In R2008b, these custom code parameters are migrated to the Configuration Parameters dialog box. Therefore, if you have scripts that use the Stateflow API to configure the Target object (`rtw`) for library models, you must update your scripts to use the `get_param` and `set_param` commands instead.

For details, see “Library Models: Mapping of GUI Options from the RTW Target Dialog Box to the Configuration Parameters Dialog Box” and “Updating Scripts That Set Options Programmatically for Simulation and Embeddable Code Generation” in the Stateflow and Stateflow® Coder™ Release Notes.

Flexible Configuration Options for Referenced Models in TLC-Based Custom Targets

In R2008b, you can specify that a configuration option for a TLC-based custom target need not have the same value in a referenced model that it has in the

parent model. By default, the values must be the same in both models. For information about overriding this default, see “Controlling Configuration Option Value Agreement” in the Real-Time Workshop Embedded Coder documentation.

Optimize Floating-Point to Integer Data Type Conversions Using New Configuration Parameter

R2008b introduces a new configuration parameter to remove code that maps NaN values to integer zero, increasing efficiency of generated code for floating-point to integer or fixed-point data type conversions. See “Remove code from floating-point to integer conversions with saturation that maps NaN to zero” in the Simulink documentation for more information.

New and Enhanced Demos

The following demo has been added:

Demo...	Shows How You Can...
rtwdemo_rtiostream	Implement a communication channel to enable exchange of data between different processes (for example, for host/target communication during Processor-in-the-Loop or External Mode simulation).

Version 7.1.1 (R2008a+) Real-Time Workshop Software

This table summarizes what's new in V7.1.1 (R2008a+):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
No	No	Bug Reports Includes fixes	No

Version 7.1 (R2008a) Real-Time Workshop Software

This table summarizes what's new in V7.1 (R2008a):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	Bug Reports Includes fixes	No

New features and changes introduced in this version are

- “Removed Static Libraries `rtwlib_*` to Simplify Code Integration” on page 23
- “New API for Registering Hardware Device Vendor and Type” on page 23
- “More Cases Supported for Rate Transition Block Automatic Insertion” on page 24
- “Removed Limitations for Number of Referenced Models Built” on page 24
- “BuildInfo API Now Provides Composite Model Reference Description” on page 24
- “BuildInfo API Better Supports Non-Compiled Dependencies” on page 24
- “MATLAB Editor Syntax Highlighting for Target Language Compiler (TLC) Code” on page 25
- “New Configuration Option “Include custom source code” for S-Function Target” on page 25
- “New Configuration Objects for Specifying Constant Function Inputs to `emlc`” on page 25
- “`emlc` Searches Directories in Different Order” on page 25
- “Generated Code No Longer Automatically Includes `math.h` Header File” on page 26

- “Default TCP/IP Transport for External Mode Uses New Server (Target) Side Communication Interface” on page 27
- “Model Referencing Not Supported with ASAM-ASAP2 Data Definition Target” on page 28
- ““What’s This?” Context-Sensitive Help Available for Simulink Configuration Parameters Dialog” on page 28
- “New and Enhanced Demos” on page 28

Removed Static Libraries `rtwlib_*` to Simplify Code Integration

In previous releases, the Real-Time Workshop software provided additional source files and functions for use in building your code in the `matlabroot/rtw/c/libsrc` directory. During code generation, these files were added to the build process. Continuing reductions of static file dependencies that began in R2007a, this release completely removes static libraries `rtwlib_*.lib/a` from the product, leaving no C source files under `matlabroot/rtw/c/libsrc`. Instead, these functions and files are generated only when needed. This reduces the number of additional source files required to compile and build the code, which improves compile time and can simplify code integration and verification.

New API for Registering Hardware Device Vendor and Type

This release provides a hardware device registration API that allows you to add “Device vendor” and “Device type” values to the default set that is displayed on the “Hardware Implementation Pane” of the Configuration Parameters dialog box.

To use this API, you create an `sl_customization.m` file, located in your MATLAB path, that invokes the `registerTargetInfo` function and fills in a hardware device registry entry with device information. The device information will be registered with Simulink software for each subsequent Simulink session.

For more information, see “Registering Additional Device Vendor and Device Type Values” in the Real-Time Workshop documentation.

More Cases Supported for Rate Transition Block Automatic Insertion

Auto-insertion of Rate Transition blocks is now supported for additional rate transitions, such as sample times with nonzero offset, and between non-integer-multiple sample times.

Additionally, as described in “Rate Transition Block Enhancements” in the Simulink Release Notes, this release allows you to

- Control the level of data transfer determinism when auto-insertion of Rate Transition blocks is selected for your model
- Specify Rate Transition block output port sample time as a multiple of input port sample time

Removed Limitations for Number of Referenced Models Built

In previous releases, Microsoft® Windows® imposed a limit on the number of models that could be referenced in a model hierarchy. This limitation is removed in R2008a. Under Microsoft Windows, as on all other platforms, the number of referenced models that can appear in a model hierarchy is effectively unlimited. See “Generating Code for Model Referencing” for information about model referencing.

BuildInfo API Now Provides Composite Model Reference Description

In previous releases, the model build information set up and managed using the `RTW.BuildInfo` API did not include source files for referenced models. In this release, the `packNGo` function supports a full model reference hierarchy, and zip files created using `packNGo` now include source files for referenced models.

BuildInfo API Better Supports Non-Compiled Dependencies

In this release, the `RTW.BuildInfo` API adds the following functions for handling non-compiled files, such as DLL files required for a final executable, or a README file:

<code>addNonBuildFiles</code>	Add nonbuild-related files to model's build information
<code>getNonBuildFiles</code>	Nonbuild-related files from model's build information

MATLAB Editor Syntax Highlighting for Target Language Compiler (TLC) Code

In R2008a, syntax highlighting is available for TLC code. For details, see “Setting TLC Language Preferences” in the MATLAB documentation.

New Configuration Option “Include custom source code” for S-Function Target

This release adds the model configuration option **Include custom source code**, which allows you to include custom source code in the code generated for the Real-Time Workshop S-function target (`rtwsfcn.tlc`). This option is located on the **Real-Time Workshop S-Function Code Generation Options** pane of the Configuration Parameters dialog box. See “Real-Time Workshop Pane: Real-Time Workshop S-Function Code Generation Options” in the Real-Time Workshop reference documentation for more information.

New Configuration Objects for Specifying Constant Function Inputs to `emlc`

When you know primary inputs will not change at runtime, you can specify them as constant values using `emlcoder.Example` and `emlcoder.egc` to eliminate overhead in generated code. See “Specifying Constant Inputs Using the `-eg` Option” in the Real-Time Workshop documentation.

`emlc` Searches Directories in Different Order

When you use the `-I` option to add directories to the Embedded MATLAB path, `emlc` now searches directories from left to right. This behavior matches C compilers such as `gcc` and the MATLAB compiler `mcc`.

Compatibility Considerations

In previous releases, the search order was from right to left. The change may produce unexpected results if you use `emlc -I` with overloaded functions. For example, suppose you specify two directories on the `-I` argument list, where each directory contains a file named `myFcn.m`, as follows:

```
emlc -I 'dir1;dir2' myFcn.m
```

In this release, `emlc` adds `myFcn.m` from `dir1` to the Embedded MATLAB path. In previous releases, `dir2` took precedence.

Generated Code No Longer Automatically Includes `math.h` Header File

In previous releases, code generated by the Real-Time Workshop software automatically included the `math.h` header file, defining C standard math functions, regardless of the math requirements of the target environment. In this release, selecting a target function library (TFL) for your model controls which header files are included, and the generated code does not automatically include `math.h` unless your model contains a floating-point math function that requires it. For more information about selecting TFLs, see “Selecting and Viewing Target Function Libraries” in the Real-Time Workshop documentation.

Compatibility Considerations

If you have created an inlined S-function that implicitly relies on the `math.h` provided by The MathWorks, and if the generated code for your model no longer includes `math.h`, you will need to update the TLC file for your S-function to explicitly include `math.h`. For example, you can add the following line to a `BlockInstanceSetup`, `BlockTypeSetup`, or `Outputs` function in your S-function TLC file:

```
%<LibAddToCommonIncludes("math.h")>
```

For more information, see `LibAddToCommonIncludes(incFileName)` and “Block Target File Methods” in the Real-Time Workshop Target Language Compiler documentation.

Default TCP/IP Transport for External Mode Uses New Server (Target) Side Communication Interface

In previous releases, the server (target) side of the default TCP/IP transport layer for external mode communication was defined by the following files in the server side directory `matlabroot/rtw/c/src/ext_mode/`:

- `common/ext_svr_transport.h`
- `tcpip/ext_svr_tcpip_transport.c`
- `tcpip/ext_tcpip_utils.c`

In R2008a, the default TCP/IP transport has been revised to use a new server (target) side communication interface. The server side of the TCP/IP transport layer is now defined by the following files in `matlabroot/rtw/c/src/ext_mode/`:

- `common/rtiostream.h`
- `common/rtiostream_interface.c`
- `tcpip/rtiostream_tcpip.c`

The file `tcpip/ext_svr_tcpip_transport.c` has been removed from the software and the file `ext_tcpip_utils.c` has been moved to the client (host) side directory `matlabroot/rtw/ext_mode/tcpip/`.

For details, see “Creating an External Mode Communication Channel” in the *Real-Time Workshop User’s Guide* and see the files in `matlabroot/rtw/c/src/ext_mode/`.

Compatibility Considerations

If you have custom template makefiles (TMFs) that use the default external mode TCP/IP transport layer, you must locate the `EXT_SRC` line in each TMF and replace `"ext_svr_tcpip_transport.c"` with `"rtiostream_interface.c rtiostream_tcpip.c"`. For example, given the following line:

```
EXT_SRC = ext_svr.c updown.c ext_work.c ext_svr_tcpip_transport.c
```

Change it to:

```
EXT_SRC = ext_svr.c updown.c ext_work.c rtiostream_interface.c rtiostream_tcpip.c
```

Model Referencing Not Supported with ASAM-ASAP2 Data Definition Target

The ASAM-ASAP2 Data Definition Target in Real-Time Workshop 7.1 (R2008a) does not support model referencing.

“What’s This?” Context-Sensitive Help Available for Simulink Configuration Parameters Dialog

R2008a introduces “What’s This?” context-sensitive help for parameters that appear in the Simulink Configuration Parameters dialog. This feature provides quick access to a detailed description of the parameters, saving you the time it would take to find the information in the Help browser.

To use the “What’s This?” help, do the following:

- 1 Place your cursor over the label of a parameter.
- 2 Right-click. A **What’s This?** context menu appears.

For example, the following figure shows the **What’s This?** context menu appearing after a right-click on the **Start time** parameter in the **Solver** pane.



- 3 Click **What’s This?** A context-sensitive help window appears showing a description of the parameter.

New and Enhanced Demos

The following demo has been added:

Demo...	Shows How You Can...
rtwdemo_configuration_set	Work with configuration parameters to configure a model for code generation. The demo also links to documentation of model options and provides tools and scripts to help automate model configuration.

Version 7.0.1 (R2007b+) Real-Time Workshop Software

This table summarizes what's new in V7.0.1 (R2007b+):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
No	No	Bug Reports Includes fixes	No

Version 7.0 (R2007b) Real-Time Workshop Software

This table summarizes what's new in V7.0 (R2007b):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	Bug Reports Includes fixes	No

New features and changes introduced in this version are

- “New emlC Command-Line Function for Generating C Code from Embedded MATLAB” on page 32
- “Code Generation from Embedded MATLAB Algorithms That Span Multiple M-Files” on page 32
- “Support for Stateflow Animation with Simulink External Mode” on page 33
- “Enhanced Auto-Insertion of Asynchronous Rate Transition Blocks” on page 33
- “Redundant Buffers Removed Between Asynchronous Rates with Same Priority” on page 33
- “New Configuration Parameters for Controlling Compiler Optimization Level and Specifying Custom Optimization Settings” on page 33
- “Additional Microprocessors and Enhanced Graphical Interface for Selecting Code Generation Target Hardware” on page 36
- “Enhanced Efficiency in Generated Code of Iterator-Selector-Assignment Patterns” on page 37
- “Code Optimizations for Concatenate, Conjugate, Dot Product, and Transpose Blocks” on page 38
- “Negative Expressions Enhanced Efficiency in Generated Code” on page 38
- “Expression Folding Enhancement” on page 38

- “Static File Dependencies Reduced for Improved Integration and Builds” on page 39
- “Support for Selecting and Viewing a Target Function Library (TFL)” on page 39
- “Real-Time Workshop Reserved Keywords Listed in Documentation” on page 40
- “Template Makefile Token ADD_MDL_NAME_TO_GLOBALS Removed” on page 40
- “Nonzero Start Time Behavior Change” on page 40
- “TLC Custom Code Library Function Behavior Changes” on page 41
- “Template Makefile MAKECMD Path Change for gmake on Microsoft Windows” on page 42
- “New and Enhanced Demos” on page 43

New emlc Command-Line Function for Generating C Code from Embedded MATLAB

Embedded MATLAB introduces a new function, Embedded MATLAB Coder (`emlc`), that generates C code from M-code that is compliant with the Embedded MATLAB language subset. The generated C code can be packaged as an executable, library, or MEX function. For more information, see “Working with Embedded MATLAB Coder” in the Real-Time Workshop documentation.

Code Generation from Embedded MATLAB Algorithms That Span Multiple M-Files

You can now generate embeddable code for external M-functions from Embedded MATLAB. This feature allows you to call external functions from multiple locations in an M-file or model and include these functions in the generated code.

Compatibility Considerations

In previous releases, Embedded MATLAB did not compile external M-functions, but instead dispatched them to MATLAB for execution (after warning). Now, the default behavior is to compile and generate code for

external M-functions called from Embedded MATLAB. If you do not want Embedded MATLAB to compile external M-functions, you must explicitly declare them to be extrinsic, as described in “Calling MATLAB Functions” in the Embedded MATLAB documentation.

Support for Stateflow Animation with Simulink External Mode

When running Simulink models in external mode, you can now animate states and view Stateflow test points in floating scopes and signal viewers. For more information on Stateflow animation, see “Animating Stateflow Charts” in the Stateflow documentation.

Enhanced Auto-Insertion of Asynchronous Rate Transition Blocks

In previous releases, Rate Transition blocks were required to be inserted at each port of an asynchronous function call subsystem, even when unnecessary. This release provides improved auto-insertion of Rate Transition blocks for asynchronous subsystems.

Redundant Buffers Removed Between Asynchronous Rates with Same Priority

In previous releases, Rate Transition blocks between asynchronous rates with the same priority introduced superfluous buffers. This release removes the redundant buffers and allows direct signal connection between asynchronous rates with the same priority.


New Configuration Parameters for Controlling Compiler Optimization Level and Specifying Custom Optimization Settings

In previous releases, users controlled compiler optimizations for building generated code by editing compiler flags into template makefiles (TMFs) or by supplying compiler flags to the Real-Time Workshop make command.

This release adds a **Compiler optimization level** parameter that allows users more flexible and generalized control over the compiler optimization

level for building generated code. For example, you can use this parameter to trade off compilation time against run time for your model code without having to supply compiler-specific flags to other levels of the Real-Time Workshop build process.

The **Compiler optimization level** parameter appears in the **Build process** subpane of the **Real-Time Workshop** pane of the Configuration Parameters dialog box, as shown below:



The available values for the **Compiler optimization level** parameter are

- Optimizations off (faster builds)
- Optimizations on (faster runs)
- Custom — Optimize based on user-specified compiler optimization flags

The default setting is Optimizations off (faster builds) (see “Compatibility Considerations” on page 35).

Selecting the value Custom enables the **Custom compiler optimization flags** field, in which you can enter custom compiler optimization flags (for example, -O2).

For more information about the **Compiler optimization level** parameter and its values, see “Controlling Compiler Optimization Level and Specifying Custom Optimization Settings” in the Real-Time Workshop User’s Guide and “Compiler optimization level” and “Custom compiler optimization flags” in the Real-Time Workshop reference documentation.

This release also provides:

- Compiler optimization level control for Simulink simulation (see the **Optimization** pane of the Configuration Parameters dialog box)
- Command-line parameters `RTWCompilerOptimization` and `RTWCustomCompilerOptimizations` for controlling compiler optimization level from M-code
- For Real-Time Workshop Embedded Coder product users, target configuration parameter `CompOptLevelCompliant`, which allows custom embedded targets to declare whether they support compiler optimization level control

Compatibility Considerations

The default setting of the new **Compiler optimization level** parameter introduces a performance-related compatibility consideration. When building and running your model code with the default setting, you may notice shorter compilation times, but longer execution times, compared to previous releases. The degree of difference can depend on model characteristics such as model (code) size and number of time steps taken.

Note If you specified custom compiler optimization flags for your model using `OPT_OPTS`, your existing optimization settings are honored and your model behavior should not change.

In previous releases, the compiler optimization level for building Real-Time Workshop generated code was controlled for each target by compiler flags supplied in TMFs or through other Real-Time Workshop build process mechanisms. The effective compiler optimization level setting varied from target to target.


In this release, the compiler optimization level can be controlled through the **Compiler optimization level** parameter in the Configuration Parameters dialog box, which by default is set to the value `Optimizations off` (faster builds). This setting trades off code execution speed for faster code compilation.

To change the compiler optimization level for code generated from your model, change the value of the **Compiler optimization level** parameter to Optimizations on (faster runs) or Custom.


Additional Microprocessors and Enhanced Graphical Interface for Selecting Code Generation Target Hardware

In previous releases, hardware listings on the **Hardware Implementation** pane of the Configuration Parameters dialog box did not follow a consistent convention based on device vendor and type. This release introduces a two-step hardware selection process based on device vendor and device type parameters on the **Hardware Implementation** pane. To select a device in either the **Embedded hardware** subpane or the **Emulation hardware** subpane,

- 1 Select a value from the **Device vendor** list. Your selection of vendor will determine the available device values in the **Device type** list.



- 2 Select a value from the **Device type** list. Your selection will populate the device characteristics fields on the **Hardware Implementation** pane appropriately.



For more information about selecting code generation target hardware, see “Describing the Emulation and Embedded Targets” in the Real-Time Workshop documentation and “Device vendor” and “Device type” in the Simulink reference documentation.

Enhanced Efficiency in Generated Code of Iterator-Selector-Assignment Patterns

New features of the Iterator-Selector-Assignment pattern reduce the global and stack data sizes and improve the code structure and execution speed.

- Previously, a global variable was used to pass information from a Width block outside of a For Iterator subsystem into the subsystem. In R2007b, a Width block can be directly connected to a For Iterator block and embedded in a For Iterator subsystem. In this configuration, the output of the Width block is a local variable.
- In the code generated for the For Iterator block, the for loop initialization assignment occurs before entering the loop, avoiding an extra if condition in the generated code.

Code Optimizations for Concatenate, Conjugate, Dot Product, and Transpose Blocks

The Real-Time Workshop build process uses a new technique to handle matrix data, resulting in generating shorter, better performing code for the Concatenate, Conjugate, Dot Product, and Transpose blocks.

Previously, temporary buffers were created to carry concatenated signals. In R2007b, the Real-Time Workshop build process eliminates unnecessary temporary buffers and writes the concatenated signal to the downstream global buffer directly, reducing the stack size and improving code execution speed.

Negative Expressions Enhanced Efficiency in Generated Code

Previously, the Real-Time Workshop build process generated the negative expression:

```
expr * (-1)
```

In R2007b, the Real-Time Workshop build process generates a simpler expression to provide a solution that is closer to hand code.

```
-expr
```

Expression Folding Enhancement

Expression folding is enhanced to reduce the size of code and improve code execution speed. In R2007a, the expression folding code generation process created temporary variables, as shown in bold in the following example:

```
real_T rtb_Merge[12];
int32_T i;
for (i = 0; i < 12; i++) {
    if (folding_U.In3 > 0.0) {
        rtb_Merge[i] = 2.0 * In1[i];
    } else {
        rtb_Merge[i] = 3.0 * In2[i];
    }
    folding_Y.Out1[i] = rtb_Merge[i];
}
```

In R2007b, temporary variables are no longer present in the generated code and the global buffer is directly written to, as shown in bold in the following example:

```
int32_T i;
for (i = 0; i < 12; i++) {
    if (folding_U.In3 > 0.0) {
        folding_Y.Out1[i] = 2.0 * In1[i];
    } else {
        folding_Y.Out1[i] = 3.0 * In2[i];
    }
}
```

Static File Dependencies Reduced for Improved Integration and Builds

The Real-Time Workshop software provides additional source files and functions for use in building your code in the *matlabroot/rtw/c/libsrc* directory. During code generation, these files are added to the build process. Continuing reductions of static file dependencies that began in R2007a, this release removes additional source files from the *libsrc* directory. Instead, these functions and files are generated only when needed. This reduces the number of additional source files required to compile and build the code, which improves compile time and can simplify code integration and verification.

Support for Selecting and Viewing a Target Function Library (TFL)

In this release, the Real-Time Workshop Embedded Coder software introduces the Target Function Library (TFL) API for mapping math functions and operators to target-specific code. The Real-Time Workshop software supports the abilities to

- Select an existing math library to use with your model. To select a math library, go to the **Interface** pane of the Configuration Parameters dialog box and select an appropriate value from the **Target function library** drop-down list.
- View the content of target function library tables that were created using the Real-Time Workshop Embedded Coder software. To bring up the

TFL Viewer with all available math libraries listed, issue the MATLAB command `RTW.viewTfl`.

For more information, see “Selecting and Viewing Target Function Libraries”.

Real-Time Workshop Reserved Keywords Listed in Documentation

The complete list of Real-Time Workshop reserved keywords is available at “Reserved Keywords” in the Real-Time Workshop documentation.

Compatibility Considerations

Real-Time Workshop keywords are reserved for use internal to the Real-Time Workshop software or C programming, and should not be used in your model as identifiers or function names. If your model uses these keywords, you should modify your model to use words that are not reserved. If your model contains any reserved keywords, the Real-Time Workshop build does not complete and an error message is displayed.

Template Makefile Token ADD_MDL_NAME_TO_GLOBALS Removed

The `ADD_MDL_NAME_TO_GLOBALS` token is no longer available for use in template makefiles.

Compatibility Considerations

If you have the `ADD_MDL_NAME_TO_GLOBALS` token in your template makefile, the code generation make process issues an error. Remove the `ADD_MDL_NAME_TO_GLOBALS` token from all template makefiles.

Nonzero Start Time Behavior Change

Previously, the Real-Time Workshop software issued a warning when generating code for models with nonzero start time when the selected target did not support nonzero start time, and the generated code might not have operated correctly. In R2007b, when the Real-Time Workshop build process encounters this condition, the build does not complete and an error message is displayed.

For a list of targets that support nonzero start time, see “Targets Supporting Nonzero Start Time” in the *Real-Time Workshop User’s Guide*.

Compatibility Considerations

Previously, the Real-Time Workshop build process generated correct code for absolute-time independent models without error. In R2007b, before generating code, set the model start time to zero for no change in functionality of the generated code.

TLC Custom Code Library Function Behavior Changes

In R2007b, the following TLC custom code library functions behave differently:

- `LibSystemOutputCustomCode`
- `LibSystemUpdateCustomCode`
- `LibSystemInitializeCustomCode`
- `LibSystemDerivativeCustomCode`
- `LibSystemEnableCustomCode`
- `LibSystemDisableCustomCode`

Compatibility Considerations

Previously, the Real-Time Workshop build process generated correct code for TLC custom code library functions without error. In R2007b, the Real-Time Workshop build process requires all calls to TLC custom code functions to be declared in the top-level S-function `.tlc` file, otherwise the custom code function is ignored. If your top-level S-function indirectly calls a TLC custom code function, you must include the white space delimited TLC custom code function call as a TLC comment in the top-level S-function. For example, if your top-level S-function file calls another file that calls `LibSystemOutputCustomCode`, you must include the comment `%LibSystemOutputCustomCode()` in the top-level S-function `.tlc` file. The Real-Time Workshop build process generates an error when it detects that a S-function indirectly calls TLC custom code functions without the required comment.

`LibSystemOutputCustomCode` and `LibSystemUpdateCustomCode` behave differently in rate-grouped and non-rate-grouped code generation modes when called from a block output or update function. The system's output and update custom code is no longer duplicated if it has been registered by a block in the output or update function in a rate-grouped multirate system. The custom code is executed for all rates in rate-grouped single-tasking modes, and is executed once in non-rate-grouped multitasking modes. The old behavior is preserved if the block registers the custom code for the parent system's output or update function in TLC block functions other than output and update, for example `BlockInstanceSetup`. This ensures the custom code block library works the same as in previous releases. The behavior of the Real-Time Workshop custom code block library remains unchanged.

Template Makefile MAKECMD Path Change for gmake on Microsoft Windows

In R2007b, Windows template makefiles (TMFs) that use `gmake (*_lcc.tmf)` specify a different path to `make` than in previous releases.

Compatibility Considerations

If you have customized a Windows TMF that uses gmake, update your TMF for the path change by removing \rtw from the MAKECMD line. For example, change

```
MAKECMD          = "%MATLAB%\rtw\bin\win32\gmake"
```

to

```
MAKECMD          = "%MATLAB%\bin\win32\gmake"
```

New and Enhanced Demos

The following demo has been added:

Demo...	Shows How You Can...
rtwdemo_emlcbasicdemo	Use Embedded MATLAB Coder (emlc) to generate embeddable C code from M-code, compile, run and view the generated C code, and display the results.

Version 6.6.1 (R2007a+) Real-Time Workshop Software

This table summarizes what's new in V6.6.1 (R2007a+):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
No	No	Bug Reports Includes fixes	No

Version 6.6 (R2007a) Real-Time Workshop Software

This table summarizes what's new in Version 6.6 (R2007a):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	Bug Reports Includes fixes	Current product documentation

New features and changes introduced in this version are

- “Static File Dependencies Reduced For Improved Integration and Builds” on page 46
- “Support for Simulink Legacy Code Tool Enhancements” on page 46
- “New Target Language Compiler Tutorial” on page 48
- “Code Generation for Multidimensional Signals” on page 48
- “Enhanced Checking and Reporting for Identifier Conflicts” on page 48
- “Enhanced Support for Tunable Parameters in Expressions” on page 49
- “New Loss of Tunability Diagnostic” on page 49
- “Support for Microsoft® Visual C++ Express Edition” on page 49
- “Enhanced Code Efficiency, Including Merge Block Optimizations” on page 49
- “Reporting of Unconnected Signal Generators” on page 50
- “Real-Time Workshop Profiling Works with Referenced Models” on page 50
- “New Makefile Command Controls Location and Naming of Model Reference Libraries” on page 50
- “New TMF Token MODELREF_LINK_RSPFILE Supports Linking Response Files for Model Reference” on page 50

- “New `sl_customization` Based Method for Registering External Mode Transport Layers” on page 51
- “New and Enhanced Demos” on page 51

Static File Dependencies Reduced For Improved Integration and Builds

The Real-Time Workshop software provides additional source files and functions for use in building your code in the `matlabroot/rtw/c/libsrc` directory. During code generation, these files are added to the build process. This release removes over 200 source files from the `libsrc` directory. Instead, these functions and files are generated only when needed. This reduces the number of additional source files required to compile and build the code, which improves compile time and can simplify code integration and verification.

Support for Simulink Legacy Code Tool Enhancements

The Real-Time Workshop software supports the following Legacy Code Tool enhancements:

- New fields in the Legacy Code Tool data structure: `InitializeConditionsFcnSpec` and `SampleTime`.
`InitializeConditionsFcnSpec` defines a function specification for a reentrant function that the S-function calls to initialize and reset states. `SampleTime` allows you to specify whether sample time is inherited from the source block, represented as a tunable parameter, or fixed.
- Support for state (persistent memory) arguments in registered function specifications.
- Support for complex numbers specified for input, output, and parameter arguments in function specifications. This support is limited to use with Simulink built-in data types.
- Support for multidimensional arrays specified for input and output arguments in function specifications. Previously, multidimensional array support applied to parameters only.
- Ability to apply the `size` function to any dimension of function input data—input, output, parameter, or state. The data type of the `size` function’s return value can be any type except complex, bus, or fixed-point.

- A new Legacy Code Tool option, 'backward_compatibility', which you can specify with the `legacy_code` function. This option enables Legacy Code Tool syntax, as made available from MATLAB Central in releases before R2006b, for a given MATLAB session.

- The following new demos:

```
rtwdemo_lct_sampletime  
rtwdemo_lct_work  
rtwdemo_lct_cplxgain  
rtwdemo_lct_ndarray
```

For more information, see

- “Integrating Existing C Functions into Simulink Models with the Legacy Code Tool” in the Writing S-Functions documentation
- “Automating the Generation of Files for Fully Inlined S-Functions Using Legacy Code Tool” in the Real-Time Workshop documentation
- `legacy_code` function reference page

New Target Language Compiler Tutorial

The Target Language Compiler (TLC) has been updated and includes a new tutorial that provides new users with an introduction to TLC syntax. See “Target Language Compiler Tutorials” for more information.

Code Generation for Multidimensional Signals

The Real-Time Workshop software now supports code generation for multidimensional signals. For more information, see “Multidimensional Signals” in the Simulink release notes.

Enhanced Checking and Reporting for Identifier Conflicts

The Real-Time Workshop software supports the following identifier conflict enhancements:

- Performance improvement: For large models, the Real-Time Workshop software reviews 100 times more identifiers while delivering the same performance as in R2006a.
- MISRA® compliance: All model reference identifiers and all reused subsystem identifiers comply with MISRA guidelines.

- Conflict detection: A more unified conflict detecting and reporting mechanism checks more identifiers, providing more information when conflicts occur.

Enhanced Support for Tunable Parameters in Expressions

Expressions that index into tunable parameters, such as $P(1)+P(2)/P(i)$, retain their tunability in generated code, including simulation code that is generated for a referenced model. Both the indexed parameter and the index itself can be tuned.

Parameter expressions of the form $P(i)$ retain their tunability if all of the following are true:

- The index i is a constant or variable of double data type
- P is a 1D array, or a 2D array with one row or one column, of double data type
- P does not resolve to a mask parameter, but to a variable in the model or the base workspace

New Loss of Tunability Diagnostic

Previously, any loss of tunability generated a warning. In R2007a, you can use the **Loss of Tunability** diagnostic to control whether loss of tunability is ignored or generates a warning or error. See “Detecting Loss of Tunability” for details.

Support for Microsoft Visual C++ Express Edition

The Real-Time Workshop software now supports using Microsoft® Visual C++® Express Edition for compilation.

Enhanced Code Efficiency, Including Merge Block Optimizations

The Merge block adds support for dead code elimination of its inputs. For any Merge block input port that is connected to an unconditionally executed block, dead code elimination removes the calculation of unused values.

Reporting of Unconnected Signal Generators

During code generation, the Signal & Scope Manager reports unconnected signal generators.

Real-Time Workshop Profiling Works with Referenced Models

You can now use Real-Time Workshop Profiling with referenced models, which was not possible in previous releases.

New Makefile Command Controls Location and Naming of Model Reference Libraries

Except on the Apple® Macintosh® platform, you can use the makefile command `USE_MDL_LIBPATHS` to change the Real-Time Workshop default location and naming for model reference libraries. See “Controlling the Location of Model Reference Libraries” for details.

New TMF Token `MODELREF_LINK_RSPFILE` Supports Linking Response Files for Model Reference

R2007a adds the template makefile (TMF) token `MODELREF_LINK_RSPFILE` for use with model reference. The `MODELREF_LINK_RSPFILE` token for the top-level model expands to the name of a response file that the top-level model links against. This token is valid only for build environments that support linker response files.

`MODELREF_LINK_RSPFILE` offers a preferred alternative to the token `MODELREF_LINK_LIBS`, which expands to a list of referenced model libraries that the top-level model links against, provided that the linker supports response files.

For more information, see “Supporting Optional Features” in the Real-Time Workshop Embedded Coder documentation.

New sl_customization Based Method for Registering External Mode Transport Layers

This release introduces a new method for registering external mode transport layers with the Simulink software. To register a TCP/IP or serial transport layer with a custom target, or to register a custom transport layer, you must add an entry of the following form to an `sl_customization.m` file on the MATLAB path:

```
function sl_customization(cm)
    cm.ExtModeTransports.add('stf.tlc', 'transport', 'mexfile', 'Level1');
%end function
```

For more information about using the new transport registration method with custom targets and/or custom transport layers, see “Client/Server Implementations” and “Creating an External Mode Communication Channel” in the *Real-Time Workshop User’s Guide*.

Compatibility Considerations

In previous releases, external mode transport layers were associated with targets based on target class, so that a custom target derived from a MathWorks GRT or ERT target by default would inherit its external mode transport layers.

Beginning in this release, external mode transport layers are associated with targets based on system target file name rather than target class. In order to support external mode, custom targets that previously inherited transport layers based on target class now must specify `cm.ExtModeTransports.add` lines in an `sl_customization.m` file on the MATLAB path, as shown above.

New and Enhanced Demos

The following demos have been added:

Demo...	Shows How You Can...
<code>rtwdemo_lct_sampletime</code>	Specify whether sample time is inherited from the source block, represented as a tunable parameter, or fixed

Demo...	Shows How You Can...
<code>rtwdemo_lct_work</code>	Use state arguments in registered function specifications
<code>rtwdemo_lct_cplxgain</code>	Specify complex numbers for input, output, and parameter arguments in function specifications.
<code>rtwdemo_lct_ndarray</code>	Specify multidimensional arrays for input and output arguments in function specifications.

Version 6.5 (R2006b) Real-Time Workshop Software

This table summarizes what's new in Version 6.5 (R2006b):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	Bug Reports Includes fixes	No

New features and changes introduced in this version are

- “Support for Simulink® Report Generator” on page 54
- “New Pack-and-Go Utility” on page 54
- “Support for New Simulink.SubSystem.getChecksum Command for Determining Why Subsystem Code Is Not Reused” on page 55
- “Merge Block Input Signals Can Have Storage Classes” on page 55
- “Code Formatting Consistency Improvements” on page 56
- “Support for Simulink Legacy Code Tool” on page 56
- “New findIncludeFiles Function” on page 56
- “Show eliminated statements Model Configuration Option Renamed” on page 57
- “Change to Default Settings for Multitasking Diagnostic Options” on page 57
- “Parameter Pooling Is Now Always Enabled” on page 58
- “PreLookup Index Search and Interpolation (n-D) Using PreLookup Block Changes” on page 59
- “Character Patterns You Should Not Use in Block Names” on page 59
- “New and Enhanced Demos” on page 60

Support for Simulink Report Generator

The Real-Time Workshop software has added support for the Simulink® Report Generator™. You can use the Simulink Report Generator to document a code generation project in a variety of output formats: Rich Text Format (RTF), Extensible Markup Language (XML), and Hypertext Markup Language (HTML). By using the Real-Time Workshop `codegen.rpt` setup file and the components Code Generation Summary and Import Generated Code, you can generate a report that includes

- Model name and version
- Real-Time Workshop product version
- List of generated source and header (include) files
- Optimization and Real-Time Workshop target selection and build process configuration settings
- Mapping of subsystem numbers to subsystem labels for models that include subsystems
- Listings of generated and custom code for the model

To see how the Report Generator fits into the general Real-Time Workshop workflow, see “Workflow for Developing Applications Using Real-Time Workshop Software”. For details on using the Report Generator with the Real-Time Workshop product, see the tutorial in “Documenting a Code Generation Project”. See `rtwReport` for a description of the Real-Time Workshop function for generating a report from the MATLAB command line or from a script. For descriptions of the new Real-Time Workshop Report Generator components, see Code Generation Summary and Import Generated Code in the Simulink Report Generator documentation. For details on using Report Generator, see the Simulink Report Generator documentation.

New Pack-and-Go Utility

The Real-Time Workshop V6.5 (R2006b) software introduces a new pack-and-go utility that you can use to relocate static and generated code files for a model to another development environment, such as a secure system or an integrated development environment (IDE) that does not include MATLAB and Simulink. This utility uses the tools for customizing post code generation build processing and a `packNGO` function to find and package all files needed

to build an executable image for a model into a compressed file that you can relocate and unpack using a standard zip utility.

For more information on how to use the new utility, see “Relocating Code to Another Development Environment”.

Support for New `Simulink.SubSystem.getChecksum` Command for Determining Why Subsystem Code Is Not Reused

The V6.5 (R2006b) Real-Time Workshop software supports a new `Simulink.SubSystem.getChecksum` command that you can use to determine why subsystem code is not reused.

For a discussion on the code generation aspects of this feature, see “Determining Why Subsystem Code Is Not Reused” in the Real-Time Workshop documentation. For a description of the command, see `Simulink.SubSystem.getChecksum` in the Simulink documentation.

Merge Block Input Signals Can Have Storage Classes

In previous releases, an input signal connected to a Merge block could not specify any storage class except Auto. In R2006b, an input signal connected to a Merge block can specify a non-Auto storage class. This class must be the same for every non-Auto input or output signal connected to the block.

For information about the Merge block, see the Merge reference page in the Simulink documentation. For details about using Merge block signal storage classes in generated code, see the bullet for the Merge block under Other Optimization Tools and Techniques in the Real-Time Workshop documentation.

Code Formatting Consistency Improvements

The Real-Time Workshop software is enhanced to apply a more consistent formatting style to the code that it generates, including integrated custom code. The new style rules for code generation formatting pertain to

- Comments
- Blank lines and spaces
- Indentation
- Line breaks
- International characters
- `#define` statements
- Function definitions
- Branching and looping structural statements
- Structure definition and value initialization statements

Compatibility Considerations

No code generation readability enhancement affects the syntax or semantics of the code. Such changes affect only the physical code appearance. Therefore, applications and correctly engineered automated tests should be unaffected by any readability enhancements. However, automated tests that depended on the physical code layout may be affected. You should change such tests to operate only on functional properties of the code.

Support for Simulink Legacy Code Tool

The Real-Time Workshop software provides code generation support for the new Simulink Legacy Code Tool. This tool speeds the creation of S-functions from legacy C or C++ code. For a list of related demos, see “New and Enhanced Demos” on page 60.

New findIncludeFiles Function

A new `findIncludeFiles` function has been added to the build information API. This function searches for include (header) files in all source and include

paths recorded in a model's build information object and adds the files found, along with their full paths, to the build information object.

For information on how to use the functions in the build information API, see “Customizing Post Code Generation Build Processing”.

Show eliminated statements Model Configuration Option Renamed

The **Show eliminated statements** option on the **Real-Time Workshop > Comments** pane of the Configuration Parameters dialog box has been renamed to **Show eliminated blocks**. The corresponding configuration parameter `ShowEliminatedStatement` is not affected by this change.

Change to Default Settings for Multitasking Diagnostic Options

For new models created with Simulink V6.5 (R2006b) or later, the default value for the following multitasking diagnostic options on the Configuration Parameters dialog is set to error to avoid generation of code that might corrupt data or produce unpredictable behavior.

- **Diagnostics > Sample Time > Multitask conditionally executed subsystem**
- **Diagnostics > Data Validity > Data Store Memory Block > Multitask data store**

For more information about these multitasking diagnostic options, see “Diagnostics Pane: Sample Time” and “Diagnostics Pane: Data Validity” in the Simulink documentation.

Compatibility Considerations

For models created with a version of Simulink before V6.5 (R2006b), when the following conditions exist, Simulink displays a dialog box that reports the issue and suggests that you change the diagnostic setting to error, as recommended by the Model Advisor.

- The **Tasking mode for periodic sample times** option on the Configuration Parameters **Solver** pane is set to **MultiTasking** or the model includes an asynchronous task.
- The diagnostic setting that corresponds to the multitasking issue is set to a value other than **error**.
- You use the Real-Time Workshop software to generate code for the model.
- The Real-Time Workshop software detects a multitasking issue that might corrupt data or produce unpredictable behavior.

The dialog presents you with the following options.

Button	Action
Change	Change the diagnostic setting to error .
Ignore	Leave the diagnostic setting as is.
Always ignore	Leave the diagnostic setting as is and do not show the dialog box again.

Parameter Pooling Is Now Always Enabled

In previous releases, the **Parameter Pooling** optimization was optional and was enabled by default. Due to internal improvements, disabling **Parameter Pooling** would no longer be useful in any context. The optimization is therefore part of standard R2006b operation, and has been removed from the user interface.

Compatibility Considerations

Upgrading a model to R2006b inherently provides the effect of enabling **Parameter Pooling** in previous releases. No compatibility considerations result from this change. If the optimization was disabled in an existing model, a warning is generated when the model is first upgraded to R2006b. This warning requires no action and can be ignored.

PreLookup Index Search and Interpolation (n-D) Using PreLookup Block Changes

The Real-Time Workshop build process no longer uses the runtime library functions in `c/libsrc` to generate code for the PreLookup Index Search and Interpolation (n-D) Using PreLookup blocks. Instead, the Real-Time Workshop build process generates the lookup functions for the two blocks dynamically. In addition, if you enable the **Utility function generation** option on the **Real-Time Workshop > Interface** pane of the Configuration Parameters dialog box, the lookup functions are stored as shared utility functions.

Character Patterns You Should Not Use in Block Names

To avoid possible ambiguity in the comments in generated code, do not use the following character patterns in block names:

- `/*`
- `*/`

New and Enhanced Demos

New demos are

Demo...	Shows How You Can...
rtwdemo_codegenrpt	Use the Simulink Report Generator to automatically document code you generate with the Real-Time Workshop software.
Collection of custom code demos:	Call external legacy C and C++ functions (existing or custom code) that are external to a Simulink model. The demos use an unsupported Legacy Code Tool application programming interface (API) to register a legacy function prototype and create necessary files for an S-function that calls the specified legacy function during simulation and in generated code. The Legacy Code Tool allows you to:
rtwdemo_lct_bus	<ul style="list-style-type: none"> • Provide the legacy function specification • Generate a C MEX S-function for simulation • Generate a block TLC file and optional rtwmakecfg.m file that is used during code generation to call the legacy code
rtwdemo_lct_cpp	
rtwdemo_lct_filter	
rtwdemo_lct_fixpt_params	
rtwdemo_lct_fixpt_signals	
rtwdemo_lct_gain	
rtwdemo_lct_inherit_dims	
rtwdemo_lct_lut	
rtwdemo_lct_start_term	

Version 6.4.1 (R2006a+) Real-Time Workshop Software

This table summarizes what's new in V6.4.1 (R2006a+):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
No	No	Bug Reports at Web site	No

Version 6.4 (R2006a) Real-Time Workshop Software

This table summarizes what's new in V6.4 (R2006a):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	Bug Reports at Web site	No

New features and changes introduced in this version are

- “New Build Information Application Program Interface” on page 63
- “New Mechanism for Customizing Post Code Generation Build Processing” on page 64
- “New Model Configuration Option for Suppressing Makefile Generation” on page 64
- “New RSim Target Option for Feeding Inport Blocks with MAT-File Data” on page 65
- “Switch Block Optimization for Wide Control Port Signals” on page 65
- “Multiport Switch Block Enhanced to Generate Default Switch Case Statement” on page 65
- “C++ Language Support Enhancements” on page 66
- “Support for Simulink Signal Object Initialization” on page 67
- “Identifiers and Model Reference Applications” on page 68
- “Support for Simulink Parameter Object Data Type Enhancements” on page 68
- “Support for New Simplest Rounding Mode for Fixed-Point Simulink Blocks” on page 68
- “Name Change for PrevZC Identifier in Generated Code” on page 69

- “Format Enhancements for model.rtw File” on page 69
- “Changes to TLC Files in matlabroot/rtw/c/tlc” on page 72
- “New and Enhanced Demos” on page 73
- “Documentation Enhancements” on page 73

New Build Information Application Program Interface

V6.4 (R2006a) Real-Time Workshop introduces an application program interface (API) for populating and managing all build information associated with a given model in a single source. This feature

- Provides a mechanism for defining build information for tool chains that do not use make files
- Makes it easier to customize and maintain a model’s build information

The API includes methods for adding, managing, and retrieving:

- Compiler flags
- Preprocessor identifier definitions
- Link flags
- Include files and paths
- Source files and paths
- Libraries

The API also includes methods for updating file paths, extensions, and separators.

For information on how to use the API, see the demo `rtwdemo_buildInfo` and “Customizing Post Code Generation Build Processing” in the Real-Time Workshop documentation. For descriptions of the API methods, see “Function Reference” and “Alphabetical List”.

New Mechanism for Customizing Post Code Generation Build Processing

Starting with V6.4 (R2006a), you can customize the Real-Time Workshop build process to evaluate a post code generation command after generating and writing the model's code to disk and before generating a makefile. A post code generation command is a user-defined M-file that typically calls functions to get data from or add data to the model's build information object.

This feature is useful for applications that need to control various aspects of the build process after code generation. For example, this is necessary when you develop your own target, or you want to apply an analysis tool to the generated code before continuing with the build process.

To use this feature, you program the command as a script or function and then define the command with the new `PostCodeGenCommand` model configuration parameter.

For more information, see the demo `rtwdemo_buildInfo` and “Customizing Post Code Generation Build Processing” in the Real-Time Workshop documentation.

New Model Configuration Option for Suppressing Makefile Generation

V6.4 (R2006a) adds a new option to the **Real-Time Workshop** pane of the Configuration Parameters dialog box and a corresponding model configuration parameter, `GenerateMakefile`, which you can use to suppress makefile generation during the build process. For example, you might do this to integrate tools into the build process that are not driven by makefiles.

This option controls whether the Real-Time Workshop build process generates a makefile and is selected by default. If you clear the check box in the graphical user interface or set the parameter to `off`, the Real-Time Workshop build process does not generate a makefile for the model. When you suppress makefile generation, you must specify any post code generation processing, including compilation and linking, as a command you program and define, using the feature described in “New Mechanism for Customizing Post Code Generation Build Processing” on page 64.

For more information, see “Customizing Post Code Generation Build Processing”.

New RSim Target Option for Feeding Inport Blocks with MAT-File Data

The RSim target is enhanced with a new `-i` command line option that allows you to feed an Inport block with input data during simulation from a single MAT-file or you can change the MAT-file from one simulation to the next. The format requirements of the MAT-file data are flexible in that it can be a single time/data matrix, a single structure, or multiple structures.

For details on how to set up a MAT-file for use with an Inport block and specify signal data for an Inport block, see the demo `rtwdemo_rsim_i` and “Creating a MAT-File for an Inport Block” and “Specifying Signal Data File for an Inport Block” in the Real-Time Workshop documentation.

Switch Block Optimization for Wide Control Port Signals

In releases prior to the V6.4 (R2006a), Real-Time Workshop software optimized code generated for a Switch block such that the code for blocks connected to the data input ports executed conditionally. This optimization was limited to Switch blocks with a control port receiving scalar signals. V6.4 (R2006a) enhances Real-Time Workshop software to generate code that performs conditional branch execution whether the Switch block’s control port signal is a scalar value, a vector, or a matrix.

For a description of the Switch block, see `Switch` in the Simulink Reference.

Multiport Switch Block Enhanced to Generate Default Switch Case Statement

In V6.4 (R2006a), the Real-Time Workshop build process is enhanced to generate a default switch case statement for the Multiport Switch block. For a description of this block, see `Multiport Switch` in the Simulink Reference.

C++ Language Support Enhancements

The V6.4 (R2006a) Real-Time Workshop software adds support for C++ code generation for Signal Processing Blockset™ and Video and Image Processing Blockset™ products.

Limitations

- Microsoft Visual C and Microsoft Visual C++, GNU® C/C++, Watcom C/C++ and Borland® C/C++ compilers have been fully tested with the V6.4 (R2006a) Real-Time Workshop software and are fully supported on 32-bit Windows and 32/64-bit Linux® platforms. However, V6.4 (R2006a) provides Beta C++ support only for the Intel® C/C++ compiler, which has not yet been fully evaluated for C++ compatibility with MathWorks products.
- The Real-Time Workshop software provides Beta support for C++ code generation for all blockset products. C++ code generation for other blockset products has not yet been fully evaluated.
- The Real-Time Workshop software does not support C++ code generation for the following:

Embedded Target for Infineon® C166® Microcontrollers

Embedded Target for Motorola® MPC555

Embedded Target for Motorola HC12

Embedded Target for OSEK/VDX®

Embedded Target for TI's C2000™ DSP

Embedded Target for TI's C6000™ DSP

SimDriveline™

SimMechanics™

SimPowerSystems™

xPC Target™

- When using the model reference feature, the language of the code generated for the top model and any referenced models must match. For example, if you generate C++ code for the top model, the generated code for all referenced models must also be C++ code.
- The following Real-Time Workshop Embedded Coder dialog box fields currently do not accept the .cpp extension. However, a .cpp file will be generated if you specify a filename without an extension in these fields, with C++ selected as the target language for your generated code.

- **Data definition filename** field on the **Data Placement** pane of the Configuration Parameters dialog box
- **Definition file** field for an **mpt data object** in the Model Explorer

These restrictions on specifying .cpp will be removed in a future release.

Support for Simulink Signal Object Initialization

V6.4 (R2006a) introduces the ability to initialize Simulink signal objects with user-defined values for simulation and code generation. Data initialization increases application reliability and is a requirement of safety critical applications. Initializing signals for both simulation and code generation can expedite transitions between phases of Model-Based Design.

For details on using this feature, see the demo `rtwdemo_sigobj_iv`, “Using Signal Objects to Initialize Signals and Discrete States” in the Simulink documentation, and “Using Signal Objects to Initialize Signals and Discrete States” in the Real-Time Workshop documentation.

Compatibility Considerations

In general, if a submodel uses workspace variables and the variables change, the Real-Time Workshop build process rebuilds the submodel. This behavior also occurs if the initial value for a signal object that corresponds to a signal initialized from outside the model, such as a global data store or root input port, changes.

To work around this behavior, specify the signal object’s initial value as a tunable parameter. For example:

```
S = Simulink.Signal;  
S.InitialValue = 'K';  
K = Simulink.Parameter;  
K.Value = 4;  
K.RTWInfo.StorageClass = 'ExportedGlobal';
```

You can then use the tunable parameter to change the signal’s initial value without triggering a subsystem build.

Identifiers and Model Reference Applications

As of Version 6.4 (R2006a), to avoid name clashes in models that use model referencing, do one of the following:

- Increase the maximum identifier length setting for top and referenced models until the following warning disappears:

```
"Warning: Insufficient space for computing symbol names in  
model ...",
```

In this case, uniqueness of model names ensures that the names do not clash.

- If you have a Real-Time Workshop Embedded Coder license, you can define a unique symbol naming scheme for each model. For example, you might define 'm1\$R\$N\$M' for the first model, 'm2\$R\$N\$M' for the second model, and so forth. The uniqueness of the naming scheme prevents name clashing.

Support for Simulink Parameter Object Data Type Enhancements

The V6.4 (R2006a) Real-Time Workshop software supports the following Simulink parameter object data type enhancements discussed in “Data Type Property of Parameter Objects Now Settable” and “Range-Checking for Parameter and Signal Object Values” in the Simulink Release Notes.

- Support for fixed-point data types
- Ability to specify the data type attribute independently of the object’s value attribute

For a discussion on the code generation aspects of this enhancement, see the demo `rtwdemo_paramdt` and “Generated Code for Parameter Data Types” in the Real-Time Workshop documentation.

Support for New Simplest Rounding Mode for Fixed-Point Simulink Blocks

The V6.4 (R2006a) Real-Time Workshop software supports the new **Simplest** rounding mode that is available for the **Round integer calculations toward**

parameter of some fixed-point Simulink blocks. This rounding mode attempts to reduce or eliminate the need for extra rounding code in generated code. The Simplest rounding mode is currently available for the following blocks:

- Data Type Conversion
- Product
- Lookup Table
- Lookup Table (2-D)
- Lookup Table Dynamic

For more information, see “Rounding” in the Simulink® Fixed Point™ documentation.

Name Change for PrevZC Identifier in Generated Code

In earlier releases, the identifier generated for a data item representing previous zero-crossing signal states (type `PrevZCSigStates_model`) was named inconsistently. Depending on your target configuration, the identifier could be generated as `model_PrevZCSigState` or `model_PrevZC`. In V6.4 (R2006a), the identifier is generated as `model_PrevZCSigState` across all configurations. For example, the following would appear in generated C code for a model named `mydemo` (for which zero-crossing data is relevant):

```
/* Previous zero-crossings (trigger) states */
PrevZCSigStates_mydemo mydemo_PrevZCSigState;
```

Format Enhancements for model.rtw File

Starting in V6.4 (R2006a), the Real-Time Workshop software represents data type information in the file `model.rtw` in a more compact format. This new format omits the fields `ComplexSignal`, `DataTypeIdx`, `Dimensions`, and `Width` from where they occurred in the following records.

Record	Record Type	Fields Removed
BlockOutputs	Block output ports	ComplexSignal DataTypeIdx Width

Record	Record Type	Fields Removed
Dworks	Block Dworks	ComplexSignal Width
ExternalInputs	External inputs	ComplexSignal DataTypeIdx Width
ExternalOutputs	External outputs	Width
ModelParameters	Model parameters	ComplexSignal DataTypeIdx Dimensions Width

The following topics discuss

- “New Target Language Compiler Library Functions That Support the New File Format” on page 70
- “Compatibility Considerations” on page 71

New Target Language Compiler Library Functions That Support the New File Format

In support of the new file format, V6.4 (R2006a) adds the following new Target Language Compiler (TLC) library functions for gaining access to the ComplexSignal, DataTypeIdx, Dimensions, and Width fields for a given record. You can use the new functions with the new and old file formats.

Function	Description
LibGetRecordIsComplex(rec)	Returns the value 1 if the specified record is complex, and 0 otherwise.
LibGetRecordDataTypeId(rec)	Returns the data type identifier of the specified record as an integer.

Function	Description
<code>LibGetRecordDimensions(rec)</code>	Returns the dimensions of the specified record as a vector of integers.
<code>LibGetRecordWidth(rec)</code>	Returns the width of the specified record as an integer.

Compatibility Considerations

The Target Language Compiler (TLC) includes library functions for retrieving data from fields of the `model.rtw` file. If your application retrieves data from `model.rtw` directly, that is, without using the documented TLC library functions, the application will be incompatible and will produce incorrect results. In such cases, reprogram your application to use the documented TLC library functions to retrieve data from `model.rtw`.

The following table lists the fields now omitted from `model.rtw` and the TLC library functions you can use to gain access to the fields for various types of records.

Field	Record Type	TLC Functions
ComplexSignal	Block input port	<code>LibBlockInputSignalIsComplex</code> <code>LibGetRecordIsComplex</code>
	Block output port	<code>LibBlockOutputSignalIsComplex</code> <code>LibGetRecordIsComplex</code>
	Block parameter	<code>LibBlockParameterIsComplex</code> <code>LibGetRecordIsComplex</code>
	Block Dwork	<code>LibBlockDWorkIsComplex</code> <code>LibGetRecordIsComplex</code> (Both functions return 1 or 0, which map to the old values 'yes' and 'no', respectively.)
DataTypeIdx	Block input port	<code>LibBlockInputSignalDataTypeId</code> <code>LibGetRecordDataTypeId</code>
	Block output port	<code>LibBlockOutputSignalDataTypeId</code> <code>LibGetRecordDataTypeId</code>

Field	Record Type	TLC Functions
Dimensions	Block parameter	LibBlockParameterDataTypeId LibGetRecordDataTypeId
	Block Dwork	LibBlockDWorkDataTypeId LibGetRecordDataTypeId
	Block input port	LibBlockInputSignalDimensions LibGetRecordDimensions
	Block output port	LibBlockOutputSignalDimensions LibGetRecordDimensions
Width	Block parameter	LibBlockParameterDimensions LibGetRecordDimensions
	Block input port	LibBlockInputSignalWidth LibGetRecordWidth
	Block output port	LibBlockOutputSignalWidth LibGetRecordWidth
	Block parameter	LibBlockParameterWidth LibGetRecordWidth
	Block Dwork	LibBlockDWorkWidth LibGetRecordWidth

For descriptions of the new functions `LibGetRecordIsComplex`, `LibGetRecordDataTypeId`, `LibGetRecordDimensions`, and `LibGetRecordWidth`, see “New Target Language Compiler Library Functions That Support the New File Format” on page 70. For descriptions of other functions listed in the preceding table, see “TLC Function Library Reference” in the Real-Time Workshop Target Language Compiler documentation.

Changes to TLC Files in `matlabroot/rtw/c/tlc`

TLC files in the directory `matlabroot/rtw/c/tlc` have changed.

You should not customize TLC files in this directory even though the capability exists to do so. Such TLC customizations might not be applied during the code generation process and can lead to unpredictable results.

Compatibility Considerations

Customizations to the files in *matlabroot/rtw/c/tlc* are not compatible across releases. If you have customized TLC files that reside in that directory, you must reapply your customizations when you upgrade.

New and Enhanced Demos

New demos are

Demo...	Shows How You Can...
<code>rtwdemo_buildInfo</code>	Customize post code generation build processing by using the new build information API and new post code generation command
<code>rtwdemo_paramdt</code>	Control the data type of tunable parameters in code that the Real-Time Workshop software generates
<code>rtwdemo_rsim_i</code>	Use the new <code>-i</code> RSim target option to feed Inport blocks with MAT-file data
<code>rtwdemo_sigobj_iv</code>	Initialize Simulink signal objects with the new Simulink signal object initialization feature

The following demos have been enhanced:

- `rtwdemo_rsim_batch_script`

Documentation Enhancements

- New reference documentation — Real-Time Workshop Reference
- New tables that summarize dependencies of optimization and interface model configuration parameters
- “Running Rapid Simulations” — reorganized to reflect workflow

Version 6.3 (R14SP3) Real-Time Workshop Software

This table summarizes what's new in V6.3 (R14SP3):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	Bug Reports at Web site	No

New features and changes introduced in this version are

- “New `rtw_precompile_libs` Function” on page 75
- “Support for Subsystem Latch Enhancements” on page 75
- “Support for Variable Transport Delay Enhancements” on page 76
- “C++ Target Language Support for the Real-Time Windows Target Product and External Mode” on page 76
- “Rapid Simulation Target Enhanced for Use with the Distributed Computing Toolbox Product” on page 77
- “Simulink Model and MATLAB Desktop Window Interaction Enhanced” on page 77
- “Customizations to Built-In Blocks” on page 77
- “Use `slbuild` Instead of `rtwgen`” on page 77
- “Model Hardware Configuration Parameters Now Honor Device Type Restrictions” on page 78
- “`rem` Function No Longer Supports Tunable Arguments” on page 79
- “Block Libraries, RSim Target Executables, and MAT-Files” on page 79
- “Documentation Enhancements” on page 79

New `rtw_precompile_libs` Function

The V6.3 (R14SP3) Real-Time Workshop product introduces a new M-file function, `rtw_precompile_libs`, which you can use to

- Precompile new or updated S-function libraries (MEX-files) for a model. By precompiling S-function libraries, you can optimize system builds. Once your precompiled libraries exist, the Real-Time Workshop build process can omit library compilation from subsequent builds. For models that use numerous libraries, the time savings for build processing can be significant.
- Recompile precompiled libraries included as part of the Real-Time Workshop product, such as `rtwlib` or `dsplib`. You might consider doing this if you need to customize compiler settings for various platforms or environments.

For details on using `rtw_precompile_libs`, see “Precompiling S-Function Libraries” in the Real-Time Workshop documentation.

Support for Subsystem Latch Enhancements

The V6.3 (R14SP3) Real-Time Workshop software supports Simulink latch enhancements for triggered and function-call subsystems discussed in “Input Port Latching Enhancements” in the Simulink Release Notes.

- A renamed Inport block option is available for triggered subsystems. **Latch (buffer) input** was renamed to **Latch input by delaying outside signal** to better reflect the option’s purpose.
- A new option, **Latch input by copying inside signal**, was added for the Inport block for use with function-call subsystems.

If you select **Latch input by copying inside signal** for a function-call subsystem, the Real-Time Workshop build process

- Preserves latches in generated code regardless of any optimizations that might be set
- Places the code for latches at the start of a subsystem’s output/update function

For more detail, see the description of the Inport block.

Support for Variable Transport Delay Enhancements

The V6.3 (R14SP3) Real-Time Workshop software supports new Simulink enhancements to the Variable Transport Delay block. Prior to V6.3 (R14SP3), the block performed a variable time delay function. The block has been enhanced to support both variable time and variable transport delays with a new parameter **Select delay type**.

- For instances of the block in existing models, **Select delay type** is set to **Variable time delay** to preserve the block's variable time delay behavior. In such cases, you can use the block as is, or consider changing the parameter settings for transport delay behavior.
- The Simulink Library Browser now offers a Variable Time Delay block and Variable Transport Delay block, which are instances of the original Variable Transport Delay block. Both blocks have the delay type parameter, which is preset depending on the type of block you include. In addition, for the Variable Time Delay block, you can select a parameter for handling zero delays. For the Variable Transport Delay block, you can specify a fixed buffer size and absolute tolerance.

For more detail, see the descriptions of the Variable Time Delay and Variable Transport Delay blocks.

C++ Target Language Support for the Real-Time Windows Target Product and External Mode

The V6.3 (R14SP3) Real-Time Workshop software supports

- C++ code generation for Real-Time Windows Target™
- The use of external mode with executables it generates from C++ source files

For more information on C++ target language support, see “Support for C and C++ Code Generation” in the Real-Time Workshop documentation.

Rapid Simulation Target Enhanced for Use with the Distributed Computing Toolbox Product

The Rapid Simulation (RSim) target has been enhanced such that RSim executables that specify a variable step solver do not check out a Simulink license when run by a worker executing a task created by the Distributed Computing Toolbox™ product.

Simulink Model and MATLAB Desktop Window Interaction Enhanced

In V6.3 (R14SP3) of the Real-Time Workshop product, the interaction between Simulink model and MATLAB desktop windows during code generation has been enhanced such that the window layering and input focus during code generation on Microsoft Windows systems matches that of Linux systems.

Prior to V6.3 (R14SP3), if you had a Simulink model window on top of the MATLAB desktop window on a Windows system, the MATLAB desktop window would move on top of the model window when you generated code for that model. When code generation was complete, the MATLAB desktop window would retain input focus. This behavior intentionally differed from the behavior on Linux systems, which kept the model window on top.

Customizations to Built-In Blocks

The MathWorks recommends that you not customize built-in blocks provided as part of the Simulink product even though the capability exists to do so.

Compatibility Considerations

Customizations that you make to built-in Simulink blocks might not be applied during the code generation process and can lead to unpredictable results.

Use `slbuild` Instead of `rtwgen`

The Target Language Compiler documentation for V6.2 (R14SP2) and earlier recommends using the `rtwgen` and `tlc` commands together to create targets and generate code. Instead, you should use the `slbuild` command.

Compatibility Considerations

The `rtwgen` command is not intended for direct use, and upgrading the Real-Time Workshop product may cause code that uses the command to fail. Existing code that uses `rtwgen` should change to use `slbuild` instead, and new code should use `slbuild` exclusively. The syntax for `slbuild` is

```
slbuild('model'[, 'TargetType'])
```

Use of the `tlc` command is unaffected by this change.

Model Hardware Configuration Parameters Now Honor Device Type Restrictions

Prior to V6.3 (R14SP3), the Real-Time Workshop software allowed you to use `set_param` to modify model hardware configuration settings such that they did not conform to device type restrictions. In V6.3 (R14SP3), the Real-Time Workshop software honors device type requirements associated with the following configuration parameters:

```
ProdBitPerLong  
ProdBitPerChar  
ProdBitPerInt  
ProdBitPerShort  
ProdIntDivRoundTo  
ProdShiftRightIntArith  
ProdWordSize  
ProdEndianness  
TargetBitPerLong  
TargetBitPerChar  
TargetBitPerInt  
TargetBitPerShort  
TargetIntDivRoundTo  
TargetShiftRightIntArith  
TargetWordSize  
TargetEndianness
```

If you attempt to reset one of these parameters, the Real-Time Workshop build process returns an error.

Compatibility Considerations

If you set model parameters programmatically, check for and remove instances of `set_param` that specify the preceding parameters.

rem Function No Longer Supports Tunable Arguments

In V6.3 (R14SP3), the `rem` function no longer supports tunable parameters when used with the Real-Time Workshop software.

Compatibility Considerations

If you use tunable parameters with the `rem` function, the Real-Time Workshop build process inlines the equivalent numeric value into the generated code in place of the tunable expression.

Block Libraries, RSim Target Executables, and MAT-Files

You can use the Real-Time Workshop product to rebuild an RSim target executable for a model that you previously created with blocks provided in an earlier release.

Compatibility Considerations

Block libraries for V6.3 (R14SP3) are not compatible with block libraries provided in earlier releases. Consequently, starting with V6.3 (R14SP3), if you rebuild an RSim target executable as noted above, you cannot use the `-p` option to run the rebuilt executable with a new MAT-file. To use new MAT-files, you need to replace the blocks in the model with blocks provided in the R14SP3 block libraries

Documentation Enhancements

The following areas of the Real-Time Workshop documentation have been corrected or enhanced:

- **Help** button on **Real-Time Workshop** pane and subpanes of the Configuration Parameters dialog box — displays help that is specific to the pane or subpane that is active

- Example index — expanded
- Model reference tutorial
- “Code Generation and the Build Process” — reorganized to reflect workflow and make key topics more accessible
- “Controlling the Location and Naming of Libraries During the Build Process” — added as a new topic
- “Tunable Expressions in Masked Subsystems”
- “Profiling Generated Code” — added as a new topic
- “Reusable Code and Referenced Models”
- “Sharing Utility Functions”
- “Data Transfer Assumptions” for rate transitions
- “Writing Noninlined S-Functions”
- “Build Support for S-Functions”
- “Checksums and the S-Function Target” — added as a new topic
- “Specifying New Signal Data File for a From File Block” when running a rapid simulation
- “Generating ASAP2 and C API Files” — added as a new topic
- “Simulink Block Support” — new reference listing Real-Time Workshop and Real-Time Workshop Embedded Coder block support for blocks available in Simulink
- Target Language Compiler documentation

Version 6.2.1 (R14SP2+) Real-Time Workshop Software

This table summarizes what's new in V6.2.1 (R14SP2+):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
No	No	Bug Reports at Web site	No

Version 6.2 (R14SP2) Real-Time Workshop Software

This table summarizes what's new in V6.2 (R14SP2):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	No	Bug Reports at Web site	No

New features and changes introduced in this version are


- “Model Advisor Enhancements” on page 82
- “Rate Transition Block Enhancements” on page 84
- “Data Store Read Block Enhancement” on page 84
- “C++ Target Language Support” on page 85
- “Support for Open Watcom 1.3 Compiler” on page 87
- “New Configuration Option for Optimizing Floating-Point to Integer Data Type Conversions” on page 87
- “Task Priority Block Parameters Renamed for Consistency” on page 88
- “New RSim Target Configuration Option” on page 88
- “LibManageAsyncCounter Function Added to asynclib.tlc Library” on page 89
- “Enhanced Documentation on Integrating Legacy and Custom Code with Generated Code” on page 89
- “Documentation Enhancements” on page 90

Model Advisor Enhancements

The Model Advisor analyzes Simulink models for optimal use of Simulink for simulation and code generation. You can customize the analysis and resulting report by selecting the checks that you want the Model Advisor to perform. The Real-Time Workshop V6.2 (R14SP2) product enhances the Model Advisor

by adding several new checks and grouping checks based on their application for simulation or code generation.

The Model Advisor dialog box now appears as follows:



For more information on the Model Advisor, see “Consulting the Model Advisor” in the Simulink documentation.

Rate Transition Block Enhancements

The Rate Transition block has been enhanced to support:

- Automatic insertion for transitions to or from asynchronous tasks. If you select the **Automatically handle data transfers between tasks** on the **Solvers** pane of the Configuration Parameters dialog, Simulink detects rate transitions and inserts Rate Transition blocks automatically to handle them for asynchronous and periodic tasks. Prior to Version 6.2, automatic block insertion for asynchronous tasks was not supported. For details, see “Rate Transition Block Options”.
- Automatic insertion for single-tasking execution mode. If you select the **Automatically handle data transfers between tasks**, Simulink detects rate transitions inserts Rate Transition blocks automatically for models that execute in single-tasking or multitasking mode. Prior to V6.2 (R14SP2), automatic block insertion for single-tasking execution mode was not supported. For details, see “Rate Transitions and Asynchronous Blocks”.
- Asynchronous rates when no priority is specified. You can set the block to one of two modes: unprotected, or data integrity with no determinism. Prior to V6.2 (R14SP2), the Rate Transition block did not ensure data integrity for asynchronous rates when the priority was not set. For details, see “Rate Transitions and Asynchronous Blocks”.

Data Store Read Block Enhancement

The code that the Real-Time Workshop build process generates for the Data Store Read block has been optimized. Prior to this V6.2 (R14SP2), the code generated for this block would copy the value of the block to a temporary variable. In V6.2 (R14SP2), the Real-Time Workshop build process eliminates the use of the temporary variable, if possible.

Consider the following model:



A section of the code generated for this model, using an earlier version of the Real-Time Workshop product would appear as follows:

```

/* local block i/o variables */

real_T rtb_DataStoreRead;

/* DataStoreWrite: '/Data Store Write' incorporates:
 *   Inport: '/In1'
 */
mdsm_opt_DWork.A = mdsm_opt_U.In1;

/* DataStoreRead: '/Data Store Read' */
rtb_DataStoreRead = mdsm_opt_DWork.A;

/* Outport: '/Out1' */
mdsm_opt_Y.Out1 = rtb_DataStoreRead;

```

Note the value of `mdsm_opt_DWork.A` is stored in the temporary variable `rtb_DataStoreRead`.

The following code fragment shows the comparable section of code generated by this release of the Real-Time Workshop product. The temporary variable `rtb_DataStoreRead` is no longer used.

```

/* DataStoreWrite: '/Data Store Write' incorporates:
 *   Inport: '/In1'
 */
mdsm_opt_DWork.A = mdsm_opt_U.In1;

/* Outport: '/Out1' incorporates:
 *   DataStoreRead: '/Data Store Read'
 */
mdsm_opt_Y.Out1 = mdsm_opt_DWork.A;

```

C++ Target Language Support

In V6.2 (R14SP2), the Real-Time Workshop product introduces support for generating C++ code. The primary use for this feature is to facilitate integration of generated code with legacy or custom user code written in C++.

For information on using this feature, see the following topics in the Real-Time Workshop documentation:

- “Choosing and Configuring a Compiler”
- “Configuring the Target Language for Generated Code”
- “Integrating C and C++ Code”

For a demo, enter `sfcdemo_cppcount` in the MATLAB Command Window. For a Stateflow example, enter `sf_cpp`.

Limitations

- Microsoft Visual C and Microsoft Visual C++ and GNU C/C++ have been fully tested and are fully supported on 32-bit Microsoft Windows and Linux platforms. However, Version 6.2 provides Beta C++ support only for the Watcom, Borland, and Intel C/C++ compilers. These compilers have not yet been fully evaluated for compatibility with MathWorks products.
- The Real-Time Workshop product provides Beta support for C++ code generation for all blockset products. C++ code generation for the blockset products has not yet been fully evaluated.
- The Real-Time Workshop software does not support C++ code generation for the following:
 - Embedded Target for Infineon C166 Microcontrollers
 - Embedded Target for Motorola MPC555
 - Embedded Target for Motorola HC12
 - Embedded Target for OSEK/VDX
 - Embedded Target for TI's C2000 DSP
 - Embedded Target for TI's C6000 DSP
 - Real-Time Windows Target
 - SimDriveline
 - SimMechanics
 - SimPowerSystems
 - xPC Target
- The Real-Time Workshop build process does not support the use of external mode with executables it generates from C++ source files.

- When using the Model Reference feature, you cannot generate C code for the parent model and C++ code for models that refer to the parent model. However, you can generate C or C++ for both the parent and referring models, or C++ code for the parent model and C code for referring models.
- The following Real-Time Workshop Embedded Coder dialog box fields currently do not accept the .cpp extension. However, a .cpp file will be generated if you specify a filename without an extension in these fields, with C++ selected as the target language for your generated code.
 - **Data definition filename** field on the **Data Placement** pane of the Configuration Parameters dialog box
 - **Definition file** field for an **mpt data object** in the Model Explorer

These restrictions on specifying .cpp will be removed in a future release.

Support for Open Watcom 1.3 Compiler

V6.2 (R14SP2) provides Beta support for the Open Watcom 1.3 compiler. The compiler has not yet been fully evaluated for compatibility with MathWorks products. However, the support files necessary for you to use the compiler with MATLAB and the MATLAB® Compiler™ are available. To configure the compiler, use the `mex -setup` function. Full support will be available in a future release.

New Configuration Option for Optimizing Floating-Point to Integer Data Type Conversions

A new option, **Remove code from floating-point to integer conversions that wraps out-of-range values**, has been added to the **Optimization** pane of the Configuration Parameters dialog box that you can use to increase the efficiency of generated code that represents floating-point to integer or fixed-point data type conversions. The option removes code that ensures that execution of the generated code produces the same results as simulation when out-of-range conversions occur. This reduces the size and increases the speed of the generated code at the cost of potentially producing results that do not match simulation in the case of out-of-range values.

Consider using this option if code efficiency is critical to your application and the following conditions are true for at least one block in the model.

- Computing the block's outputs or parameters involves converting floating-point data to integer or fixed-point data
- The block's **Saturate on integer overflow** option is disabled


For more information, see “Optimizing Code Resulting from Floating-Point to Integer Conversions” in the Real-Time Workshop documentation.

Task Priority Block Parameters Renamed for Consistency

The **Effective priorities** parameter for the Async Interrupt block and **Task priority** parameter for the Task Sync block are renamed **Simulink task priority**. In both cases, the Rate Transition block uses the parameter to generate the appropriate high-to-low or low-to-high priority transition code.

New RSim Target Configuration Option

A new option, **Force storage classes to AUTO**, has been added to the **Real-Time Workshop>RSim Target** pane of the Configuration Parameters dialog box. The option is on by default and forces all storage classes to Auto. If your application requires the use of other storage classes, such as `ExportedGlobal` or `ImportedExtern`, turn this option off. The new option appears in the **Storage Classes** section as shown in the next figure.



For more information, see “Configuring and Building a Model for Rapid Simulation”.

LibManageAsyncCounter Function Added to asynclib.tlc Library

The function `LibManageAsyncCounter` has been added to the `asynclib.tlc` TLC library. This function determines whether an asynchronous task needs a counter and manages its own timer.

Enhanced Documentation on Integrating Legacy and Custom Code with Generated Code

Documentation on integrating legacy and custom code with generated code has been enhanced.

- A new section, “Integrating Legacy and Custom Code”, summarizes the mechanisms available for integrating Real-Time Workshop generated code into an existing code base or integrating existing code into Real-Time Workshop generated code. In the later scenario, integration can be either block based or model based. The new summary can help you evaluate and choose a mechanism that best meets your application requirements and directs you to other areas of the documentation for implementation details.
- The section “Using the `rtwmakecfg.m` API to Customize Generated Makefiles” discusses new fields in the `rtwmakecfg.m` API that support the Real-Time Workshop build process for S-functions.
- A new section, “Build Support for S-Functions”, discusses the different ways of adding build information to the Real-Time Workshop build process.

Documentation Enhancements

The following areas of the Real-Time Workshop documentation have been corrected or enhanced:

- Integrating custom and legacy code
- References to and screen captures showing new and modified Configuration Parameter dialog box options
- Descriptions of `MaxStackSize` and `MaxStackVariableSize` variables
- Limitations on tunable expressions
- Limitation on Stateflow outputs (removed)
- Symbolic naming conventions for signals in generated code as documented in “Working with Data Structures”
- Parameter tuning using MATLAB commands
- How to avoid parameter configuration conflicts related to storage classes
- Example for user-defined block state names
- Parameter configuration quick reference diagram (was missing from HTML output)
- Data type considerations for tunable workspace parameters
- Definitions of top model and reference model in the context of model referencing

- Deletion of user *.c files from the Real-Time Workshop build directory
- Conditions that need to be met for a block to be considered for dead code elimination
- Writing S-functions that specify sample time inheritance
- Use of `ssSetNeedAbsoluteTime` or `ssSetNeedElapseTime` in S-functions for accessing timers
- Optimizing with expression folding
- References to the Data Object Wizard (DOW) in the context of using ASAP2
- C API for S-Functions
- External mode parameter descriptions

Version 6.1 (R14SP1) Real-Time Workshop Software

This table summarizes what's new in V6.1 (R14SP1):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	No	Fixed bugs	No

Changes from the Previous Release

The behavior of the source block dialog has changed. Note that opening a dialog for a source block causes the Simulink simulation to pause. While Simulink is paused, you can edit the parameter values. You must close the dialog to have the changes take effect and allow Simulink to continue.

Version 6.0 (R14) Real-Time Workshop Software

This table summarizes what's new in V6.0 (R14):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	Fixed bugs	No

New features and changes introduced in this version are organized by these topics:

- “Tornado Support for VxWorks Target” on page 94
- “User Interface and Configuration Enhancements” on page 94
- “Support for New Simulink Model Referencing (Model Block) Feature” on page 100
- “Signal, Parameter Handling, and Interfacing Enhancements” on page 102
- “External Mode Enhancements” on page 108
- “Code Customization Enhancements” on page 111
- “Timing-Related Enhancements” on page 117
- “GRT and ERT Target Unification” on page 121
- “Underscores No Longer Replace Spaces in Identifiers for Multi-Word Block Names” on page 131
- “Global Data Structure Identifiers for Targets Now Incorporate Model Name” on page 131
- “Support for Simulink Configuration Set Feature” on page 132
- “Hardware Configuration Parameters” on page 133
- “Enhancements and Changes that Affect Custom Targets” on page 134

- “Shared Utilities Directory and the Build Process” on page 136
- “Tornado Target Requires Macro in Template Make File” on page 139
- “Custom Storage Classes Can No Longer Be Used with GRT Targets” on page 140
- “Target Language Compiler Enhancements and Changes” on page 141
- “Documentation Enhancements” on page 143

Tornado Support for VxWorks Target


In V6.0 (R14), the Real-Time Workshop product supports Tornado® Version 2.x, which targets VxWorks® 5.x.

User Interface and Configuration Enhancements

- “New Model Explorer and Configuration Parameters Dialogs for Controlling Code Generation” on page 94
- “Generated Code Report Integrated into Model Explorer” on page 96
- “Model Advisor Helps You to Configure and Optimize Targets” on page 98
- “Real-Time Workshop Software Now Supports Intel Compiler” on page 99

New Model Explorer and Configuration Parameters Dialogs for Controlling Code Generation

This release of the Simulink product features a new user interface for simulation and code generation, called Model Explorer, which replaces the **Simulation Parameters** dialog. When you select **Model Explorer** from the **Tools** menu, the Model Explorer opens in a new window containing three panes:



The Model Explorer features three resizable, scrolling panes:


- **Model Hierarchy** pane
- **Contents** pane
- **Dialog** pane

For more information on the Model Explorer, see “The Model Explorer” in the Simulink documentation.

You can also control configurations with the standalone **Configuration Parameters** dialog. To activate this interface, a model must be open. You can summon this interface in any of three equivalent ways:

- Choose **Configuration Parameters** from the Simulation menu.
- Choose **Real-Time Workshop -> Options** from the Tools menu.
- Type **Ctrl+E**.

The **Configuration Parameters** dialog with the **Optimization** pane selected is shown in the next figure.




For details on configuration parameters for code generation, see “Choosing and Configuring Your Target”, “Adjusting Simulation Configuration Parameters for Code Generation”, and “Configuring Real-Time Workshop Code Generation Parameters” in the Real-Time Workshop documentation.

Generated Code Report Integrated into Model Explorer

You can now browse files generated by the Real-Time Workshop, Real-Time Workshop Embedded Coder, and other products directly in the Model Explorer. This capability supplements HTML code generation reporting, which was available in earlier releases.

When you generate code, or open a model that has generated code for its current target configuration in your working directory, the **Model Hierarchy** pane of Model Explorer contains a node named **Code** for *model*. Under that node are other nodes, typically called **Top Model** and **Shared Code**.

When you click **Top Model**, the **Contents of** pane lists source code files in the build directory of each model that is currently open. The next figure shows code for the vdp model.



In this example, the file `./vdp_grt_rtw/vdp.c` is being viewed. To view any file in the **Contents of** pane, click it once.

The views in the dialog pane are read-only. The code listings in that pane contain hyperlinks to functions and macros in the generated code. A hyperlink for the file being viewed sits above it. Clicking it opens that file in a text editing window where you can modify its contents. This is not something you typically do with generated source code, but in the event you have placed custom code files in the build directory, you can edit them as well in this fashion.

If an open model contains Model blocks, and if generated code for any of these models exists in the current `slprj` directory, nodes for the referenced models appear in the **Model Hierarchy** pane one level below the node for the top model. Such referenced models do not need to be open for you to browse and read their generated source files.

The node directly underneath the `Top Model` node is named `Shared Code`. It collects files in the appropriate `./slprj/target/_sharedutils` subdirectory, containing shared fixed-point utility code, if any exists.

The structure and contents of `slprj` directories are described in “Project Directory Structure for Model Reference Targets” in the Real-Time Workshop documentation.

Model Advisor Helps You to Configure and Optimize Targets


The Model Advisor (formerly called Model Assistant) is a tool that helps you configure any model to optimally achieve code generation objectives. Using it, you can quickly configure a model for code generation, and identify aspects of your model that impede production deployment or limit code efficiency. Clicking the icon labeled `Advice` on `model` in the **Model Hierarchy** pane launches the Model Advisor. This node is directly below the `Code` for `model` node, as the preceding figure shows. Clicking the `Advice` node causes the dialog pane to be labeled **Model Advisor**, and to contain a link, **Start model advisor**. When you click that link, Model Advisor opens a separate HTML window with a set of button and check box controls.

Another way to invoke Model Advisor is to type the following command in the MATLAB Command Window, specifying the name of model.

```
ModelAdvisor('model')
```

If the model (assumed to be on the MATLAB path) is not currently open, the Model Advisor opens it.

The following figure shows a Model Advisor report:



See “Getting Advice About Optimizing Models for Code Generation” in the Real-Time Workshop documentation for more information.

Real-Time Workshop Software Now Supports Intel Compiler

The Real-Time Workshop software now includes support for the Intel compiler (Version 7.1 for Microsoft Windows). The Intel compiler requires Microsoft Visual C and Microsoft Visual C++ Version 6.0 or higher to be installed.

Support for New Simulink Model Referencing (Model Block) Feature

The new Model block in the Simulink library allows one model to include another model as if it were a block. This feature, called *model reference*, works by generating code for included models that the parent model executes from a binary library file. In this release, Model reference works on all UNIX and Linux platforms (using the gcc compiler), and on Microsoft Windows PC platforms (using the lcc and Visual C++® compilers).

We call models that include Model blocks *top models*. Model referencing uses *incremental loading*. When you open a top model, any models to which it refers are not loaded into memory until they are needed or you open them.

Note To take advantage of incremental model loading, models called from Model blocks must be saved at least once with Simulink V6.0 (R14). Top and referenced models must have **Inline parameters** set on.

When running simulations, models are included in other models by generating code for them in a project directory and creating a static library file called a *simulation target* (sometimes referred to as a SIM target). When the Real-Time Workshop build process generates code for referenced models, it follows a parallel process to create whatever target (for example, GRT) you have specified (sometimes generically referred to as Real-Time Workshop targets). The Real-Time Workshop build process also stores the generated code in the project directory, although generated code for parent models is stored (as in previous releases) in a build directory at the same level as the model reference project directory.

In addition to incremental loading, the model referencing mechanism employs *incremental code generation*. This is accomplished by comparing the date, and optionally, the structure of model files of referenced models with those for their generated code to determine whether it is necessary to regenerate model reference targets. You can also force or prevent code generation via the diagnostic setting for **Rebuild options** on the **Model Referencing** pane of the Configuration Parameters dialog.

You can learn more about how Model blocks work and generate code by running the following demos:

- `mdlref_basic` — General demonstration of using Model blocks
- `mdlref_paramargs` — Passing parameters to referenced models
- `mdlref_bus` — Using bus objects to communicate signals to referenced models
- `mdlref_conversion` — Automatically converting atomic subsystems in models to models called with Model blocks.

For more information on generating code for referenced models, including using `mdlref_conversion`, see “Generating Code for Model Referencing” and “Generating Code for a Referenced Model” in the Real-Time Workshop documentation.

Compatibility Considerations for Custom Targets

If you want to adapt a custom target for code generation compatibility with the model reference features, you need to modify the target’s system target file (STF) and template makefile (TMF).

General Considerations.

- A model reference compatible target must be derived from the ERT or GRT targets.
- When generating code from a model that references another model, both the top-level model and the referenced models must be configured for the same code generation target.
- Note that the **External mode** option is not supported in model reference Real-Time Workshop target builds. If the user has selected this option, it is ignored during code generation.
- To support model reference builds, your TMF must support use of the shared utilities directory, as described in “Shared Utilities Directory and the Build Process” on page 136.

System Target File Modifications. Your STF must implement a `SelectCallback` function (see “New `SelectCallback` Function for System Target Files” on page 136). Your `SelectCallback` function must declare model reference compatibility by setting the `ModelReferenceCompliant` flag.

The callback is executed if the function is installed in the `SelectCallback` field of the `rtwgensettings` structure in your STF. The following code installs the `SelectCallback` function:

```
rtwgensettings.SelectCallback =  
    ['custom_open_callback_handler(hDlg, hSrc)'];
```

Your callback should set the `ModelReferenceCompliant` flag as follows.

```
slConfigUISetVal(hDlg, hSrc, 'ModelReferenceCompliant', 'on');  
slConfigUISetEnabled(hDlg, hSrc, 'ModelReferenceCompliant', false);
```

Template Makefile Modifications. In addition to the TMF modifications described in “Shared Utilities Directory and the Build Process” on page 136, you must modify your TMF variables and rules. See “Providing Model Referencing Support in the TMF” in the Real-Time Workshop Embedded Coder documentation for instructions.

Signal, Parameter Handling, and Interfacing Enhancements

- “New C API for Accessing Model Block Outputs and Parameter Data” on page 103
- “Back-Propagating Auto, Test-pointed Signal Labels Through Subsystem Output Ports” on page 105
- “Declaring Wide Signals, States, and Parameters as `ImportedExternPointer`” on page 105
- “Bus Creator Blocks Now Can Emit Structures” on page 106
- “New Options for Controlling Resolution of Signal Objects for Named Signals and States” on page 107
- “`CustomStorageClass` and `StorageClass` Properties Initialized Differently” on page 107

New C API for Accessing Model Block Outputs and Parameter Data

C API is a target-based Real-Time Workshop feature that provides access to global block outputs and global parameters in the generated code. Using the C API, you can build target applications that log signals, monitor signals and tune parameters while the generated code executes.


In previous releases, to access model parameters via the C API, a model-specific parameter mapping file, `model_pt.c` was generated. Similarly, to access the `BlockSignals`, `model_bio.c` is generated. The new C API improves the efficiency and capability of the interface while reducing its code size. In addition, the new API supports:

- Referenced models
- Fixed-point data
- Complex data
- Reusable code

The new interface eliminates redundant fields and also improves consistency between signal and parameter structures. For example, previously the data name was `char_T*` for signals but was `uint_T` for parameters.

The C API provides a smaller memory footprint. This is achieved by mapping information common to signals and parameters in smaller structures. An index into the structure map is provided in the actual signal or parameter structure. This allows the sharing of data across signals and parameters.

When you select the C API feature and generate code, the Real-Time Workshop build process generates two additional files, `model_capi.c` and `model_capi.h`, where `model` is the name of the model. The Real-Time Workshop build process places the two C API files in the build directory, based on settings in the Configuration Parameters dialog box. The `model_capi.c` file contains information about global block signals and global parameters defined in the generated code. The `model_capi.h` file is an interface header file between the model source code and the generated C API. You can use the information in these C API files to create your application. The next figure illustrates generated files.



For details on how to use the C API, see “Data Exchange APIs” in the Real-Time Workshop documentation.

Compatibility Considerations. The old C API is still available, but at some point will be eliminated. The following table compares the files in the two versions:

C API Files	New C API Files	Old C API Files
Data structure interface	Unified interface for signals and parameters: <i>/rtw/c/src/rtw_capi.h</i>	Signals Interface: <i>/rtw/c/src/bio_sig.h</i> Parameters Interface: <i>/rtw/c/src/pt_info.h</i>
RTModel C API Interface	<i>/rtw/c/src/rtw_modelmap.h</i>	<i>/rtw/c/src/mdl_info.h</i>
TLC files	<i>/rtw/c/tlc/mw/capi.tlc</i>	<i>/rtw/c/tlc/mw/biosig.tlc</i> <i>/rtw/c/tlc/mw/ptinfo.tlc</i>

The file *rtw_modelmap.h* defines structures for mapping data from the *rtModel* structure. The file *rtw_capi.h* provides macros for accessing the *rtModel*.

Note Because the data structures used for the different APIs can conflict, you can generate either C API or external mode interface code, but not both at once. The same holds true for ASAP2 interface code, a third data exchange option available for ERT and GRT targets.

Back-Propagating Auto, Test-pointed Signal Labels Through Subsystem Output Ports

If a signal exiting an output port of a subsystem has a storage class other than `auto`, the Real-Time Workshop software internally propagates the label on that signal backwards into the subsystem so that the code generated for the subsystem uses that signal label, which is defined outside the subsystem.

Compatibility Considerations. Before this release, signal labels were not back-propagated when the signal's storage class was `auto` and it also was test-pointed. Signal labels are now also back-propagated the if the signal is test-pointed.

Declaring Wide Signals, States, and Parameters as ImportedExternPointer

If your model declares the storage class of a signal, state, or parameter as `ImportedExternPointer`, your code must define an appropriate pointer variable.

Compatibility Considerations. In V6.0 (R14), whenever a signal state or parameter is wide, you must define the variable as a pointer to an array. In previous versions, an array of pointers was assumed. Here are the changes:

Width	Previous Versions	V6.0 (R14)
scalar	<code>double *x1</code>	<code>double *x1</code>
wide	<code>double *x2[]</code>	<code>double *x2</code>

The legacy code could define and initialize data as follows:


```
double x1_data;
double *x1 = &x1_data;
```

```
double x2_data[10];  
double *x2 = x2_data;
```

This change enables wide data declared as `ImportedExternPointer` to occupy contiguous memory locations, making this storage class useful in more contexts than previously possible.

Bus Creator Blocks Now Can Emit Structures

In past releases, you could not assign a storage class to the output of a Bus Creator block. If you select the block's new parameter **Output as structure**, the output of the block can be assigned a storage class. This enables bus signals to occupy contiguous memory. When you select this parameter, you must specify a Simulink Bus object. You can make and modify bus objects (class `Simulink.Bus`) using the Bus Editor. Type `buseditor` in the MATLAB Command Window. An example Bus Creator dialog for a block that outputs a three-element structure is shown in the next figure.



For details on working with bus and other Simulink data objects, see the “Working with Data” in the Simulink documentation.

New Options for Controlling Resolution of Signal Objects for Named Signals and States

In prior releases, the Real-Time Workshop build process attempted to resolve all signal objects in a model. Checking all named signals and states was inefficient, complicated error checking, and now has the potential to cause problems for incremental code generation for referenced models. To address these concerns, the current release provides following enhancements:

- Ports and blocks with discrete state now have a setting to indicate whether or not the port/block requires that a signal label be resolved.
- Models have a parameter to control signal resolution. This option is located on the **Diagnostics/Data Integrity** pane of the Configuration Parameters dialog box.
- A utility function, `disableautosignalresolution`, is available for converting existing models (that depended on implicit signal label resolution) to the new, more efficient approach.

CustomStorageClass and StorageClass Properties Initialized Differently

In V6.0 (R14), the Real-Time Workshop product merges functionality of custom storage classes into the standard `Simulink.Parameter` and `Simulink.Signal` classes.

Compatibility Consideration. When you instantiate the `Simulink.CustomParameter` and `Simulink.CustomSignal` classes, the `CustomStorageClass` and `StorageClass` properties do not get initialized the same way they did in V5.0 (R13).

In V5.0 (R13), the properties were initialized as:

```
CustomStorageClass = 'BitField' (1st item on the list)
StorageClass = 'Custom'
```

Starting in V6.0 (R14), the properties are initialized as:

```
CustomStorageClass = 'Default' (1st item on the list)
StorageClass = 'Auto' (custom storage class is ignored)
```

External Mode Enhancements

- “External Mode Changes May Impact Customized Makefiles and Static Main files” on page 108
- “Floating Scopes Now Work in External Mode” on page 109
- “Serial Transport Mechanism for External Mode on Microsoft Windows” on page 109
- “Upgrading Custom Transport Layers for External Mode to Single-Channel Architecture” on page 110
- “New Static Memory Allocation Option for External Mode Code Generation” on page 110

External Mode Changes May Impact Customized Makefiles and Static Main files

The `grt`, `ert`, `grt_malloc`, `rsim`, `rtwin`, and `tornado` targets support external mode. For each of these targets, the template makefiles and the system target files have been changed. In addition, the `main()` files for each target have also been modified (although `ert` may have a dynamic main, which is not affected).

Compatibility Considerations. If you have customized any of these static files or their makefiles, merge your version with those in the current release if you intend to support external mode.

The file `matlabroot/rtw/ext_mode/common/ext_main.c` has also changed slightly. In function `ExtCommMain`, the line

```
ES = (ExternalSim *)plhs
```

was changed to

```
ES = (ExternalSim *)plhs[0]
```

For `xPC Target`, the same change was made in function `mexFunction` in the file `matlabroot/toolbox/rtw/targets/xpc/internal/xpc/src/ext_main.c`.

If you created your own custom `ext_main.c` file, you need to merge this change to be compatible with the corresponding change to Simulink.

Floating Scopes Now Work in External Mode

It is now possible to use Floating Scope blocks in external mode. A new section in the **External Mode** pane, **Floating scope**, contains the following new options:

- **Enable data uploading**

Functions as an “arm trigger” button for floating scopes. When the target is disconnected, it controls whether or not to “arm when connect” the floating scopes. When already connected, it acts as a toggle button to arm/cancel trigger.

- **Duration**

Specifies the duration for floating scopes. By default it is set to auto, which picks up the value specified in the signal and triggering GUI (which by default is 1000).

The behavior of wired Scope blocks is unchanged.

Serial Transport Mechanism for External Mode on Microsoft Windows

The Real-Time Workshop product now provides code to implement both the client and server side using serial as well as TCP/IP protocols. You can use the socket-based external mode implementation provided by the Real-Time Workshop software with the generated code, provided that your target system supports TCP/IP. Otherwise, use or customize the serial transport layer option provided.

This design makes it possible for different targets to use different transport layers. The GRT, GRT malloc, ERT, RSim, and xPC targets support host/target communication via TCP/IP and RS232 (serial) and TCP/IP communication. Serial transport is implemented only for Windows 32-bit architectures.

For details on how to use the serial transport mechanism for external mode, see “Using the Serial Implementation”.

Upgrading Custom Transport Layers for External Mode to Single-Channel Architecture

In earlier releases, external mode had separate logical channels for messages and data. In the TCP/IP example source files, these channels were implemented as separate sockets. Now there is only one logical channel (socket), which handles both data and messages (both of which are now called packets).

Compatibility Considerations. Most users will not notice this change. If, however, you have created your own custom transport layer for external mode, you must modify it for the single-channel architecture. Here is a summary of the changes that you may need to make:

On the target side (see example files in *matlabroot/rtw/c/src/*):

- Rename the function `ExtWaitForStartMsgFromHost()` to `ExtWaitForStartPktFromHost()`.
- Replace the functions `ExtSetHostData()` and `ExtSetHostMsg()` with `ExtSetHostPkt()`.
- Rename the function `ExtGetHostMsg()` to `ExtGetHostPkt()`.

On the host side (see example files in *matlabroot/rtw/ext_mode/*):

- Replace the functions `ExtTargetDataPending()` and `ExtTargetMsgPending()` with `ExtTargetPktPending()`.
- Replace the functions `ExtGetTargetData()` and `ExtGetTargetMsg()` with `ExtGetTargetPkt()`.
- Rename the function `ExtSetTargetMsg()` to `ExtSetTargetPkt()`.

For complete instructions, see “Creating an External Mode Communication Channel” in the Real-Time Workshop documentation.

New Static Memory Allocation Option for External Mode Code Generation

You can now generate code for external mode such that it uses only static memory allocation ("malloc-free" code). The **Static memory allocation** check box on the GRT and ERT target configuration component, enables this

feature and activates an edit field in which you can specify the size of the static memory buffer used by external mode. The default value is 1,000,000 bytes.

Should you enter too small a value for your application, external mode issues an out-of-memory error when it tries to allocate more memory than you are allowed. In such cases, increase the value of **Static memory buffer size** and regenerate the code. Determine how much memory you need to make available, enable verbose mode on the target (by including `OPTS="-DVERBOSE"` on the make command line). As it executes, external mode displays the amount of memory it tries to allocate and the amount of memory available to it each time it attempts an allocation. Should an allocation fail, you can use this console log to adjust the value specified for **Static memory buffer size**.

For more information on this new option, see “External Mode Interface Options” in the Real-Time Workshop documentation.

Code Customization Enhancements

- “Source Code for User S-Functions Easier to Include” on page 111
- “Custom Code Block Library Enhancements” on page 112
- “Combining User C++ Files with Generated Code” on page 112
- “Preventing User Source Code from Being Deleted from Build Directories” on page 113
- “Designating Target-Specific Math Functions” on page 113
- “Hook Files Describing Hardware Characteristics No Longer Supported” on page 114

Source Code for User S-Functions Easier to Include

In prior releases, the Real-Time Workshop build process sometimes failed to find S-function source files during a build, even if they were on the MATLAB path, thus aborting the build with an error. This happened because there were no rules dynamically added to the generated makefile for handling the directories in which the S-function MEX-files were located.

Now, the Real-Time Workshop build process adds an include path to the generated makefiles whenever it finds a file named `s-function-name.h` in

the same directory as the S-function MEX-file. This directory must be on the MATLAB path.

Similarly, the Real-Time Workshop build process adds a rule for the directory when it finds a file *s-function-name.c* (or *.cpp*) in the same directory as the S-function MEX-file.

This enhancement eliminates the need to copy the S-function source file into the MATLAB current directory or to create an *rtwmakecfg.m* file in the S-function directory.

Custom Code Block Library Enhancements

The Custom Code Block library has been reinstated into the Real-Time Workshop library. The library has been simplified. You can use the blocks in subsystems as in top-level models (with minor exceptions). Custom Code blocks enable you to add your own code fragments to specific functions in the Real-Time Workshop generated source code and header files. You can include the user code in Real-Time Workshop target code generated for referenced models (via Model blocks).

Note that custom code that you include in a configuration set is ignored when building Accelerator, S-function, and model reference simulation targets.

Combining User C++ Files with Generated Code

It is now possible to incorporate user C++ files into both Real-Time Workshop and Stateflow builds. The Real-Time Workshop build process itself does not generate C++ code; it simply enables them to be called and incorporated into an executable. For examples of how to use this capability, see the following demos:

- `sf_cpp.mdl` — accessible through **Stateflow Demos** in the Help Browser.
- `sfcdemo_cppcount.mdl` — (in the `sfundemos` demo suite, accessible from Help Browser under **Simulink > Features > S-Function example**.)

Preventing User Source Code from Being Deleted from Build Directories

In V5.0 (R13), the behavior of the Real-Time Workshop product regarding handling of user source files in the build directory changed. Previously, any .c or .h files that you placed in the build directory were not deleted when you rebuilt targets. Now all foreign source files are deleted by default, but you can preserve them by following the guidelines given below.

If you put a .c or .h source file in a build directory, and you want to prevent the Real-Time Workshop build process from deleting it during the TLC code generation process, insert the string `target specific file` in the first line of the .c or .h file. For example,

```
/* COMPANY-NAME target specific file
 *
 * This file is created for use with the
 * COMPANY-NAME target.
 * It is used for ...
 */
...
```

Make sure `target specific file` is spelled correctly, and occupies the first line of the source file.

Compatibility Considerations. In addition, flagging user files in this manner prevents post-processing them to indent them along with generated source files. Auto-indenting occurred in previous releases to build directory files with names having the pattern `model_*.c` (where `*` could be any string). The indenting is harmless, but can cause differences to be detected by source control software that might trigger unnecessary updates.

Designating Target-Specific Math Functions

Target configurations can expressly specify which floating-point math library to use when generating code. The Real-Time Workshop build process uses a switchyard called the Target Function Library (TFL) to designate compiler-specific versions of math functions. The mappings created in the TFL allow C runtime library support that is specific to a compiler.

The Real-Time Workshop build process provides three different TFLs:

- `ansi_tf1_tmw.mat` — The ANSI® C library (default)
- `iso_tf1_tmw.mat` — Extensions for ISO®-C/C99
- `gnu_tf1_tmw.mat` — Extensions for GNU


You choose among them by setting the **Target floating point math environment** option on the **Real-Time Workshop/Interface** pane of the Configuration Parameters dialog box. This enables you to specify different runtime libraries for different configuration sets within a given model.

Selecting ANSI-C provides the ANSI C set of library functions. For example, selecting ANSI-C would result in generated code that calls `sin()` whether the input argument is double precision or single precision. However, if you select ISO-C, the generated code calls the function `sinf()`, which is single-precision. If your compiler supports the ISO-C math extensions, selecting the ISO-C library can result in more efficient code.

Hook Files Describing Hardware Characteristics No Longer Supported

The Real-Time Workshop product now provides a menu that includes more than 20 target processors for the purpose of identifying hardware characteristics, such as word lengths. In the previous release, this information was stored in user-supplied *hook files*, which are no longer supported.

Compatibility Considerations. When you open a preexisting model that has not been saved using the current version of Simulink, and select the **Hardware Implementation** pane of the Configuration Parameters dialog box, the following set of controls appears:



All but one of the parameters below the **Device type** menu are grayed out. This is because these characteristics have been preset for the default target (32-bit Generic), as well as for several dozen known target processors that you can select from that menu.

The Real-Time Workshop build process only reads existing hook files when a model created by the V5.0 (R13) Real-Time Workshop software is built for the first time in V6.0 (R14) without your having first specified characteristics of the **Current code generation execution hardware device** on the **Hardware Implementation** pane. If you build a model in this underspecified state, the Real-Time Workshop software scans the current directory, then the MATLAB path, for an existing hook file with the name *target_rtw_info_hook.m*. If the file is found, its instructions override the defaults in that section. You can subsequently specify any characteristic freely. If at any point prior to building the target code you specify **Current code generation execution hardware device**, the Real-Time Workshop build process ignores hook files, as hardware characteristics are now configured.


When you open a preexisting (before V6.0) model, the **Hardware Implementation** pane displays a **Configure current execution hardware device** button. This button disappears after you press it once. When code is generated (**Ctrl+B**) for the target the model specifies,

- If the target has a hook file, and the **Configure current execution hardware device** button has not yet been pressed,


- The hook file is executed and configures the fields specifying current code generation execution hardware device.
- A warning is issued to the user that the hook file was used.
- The **Configure current execution hardware device** button on the Hardware configuration dialog box is permanently removed for that model (assuming that you save the model).
- If the target has a hook file and the **Configure current execution hardware device** button has been pressed (removing it),
 - Code is generated for the target using the hardware characteristics for the current code generation execution hardware device (which can default to those of the final embedded hardware device).
 - The hook file for the target is ignored, and is from now on.
 - A warning is issued that a hook file exists but was not used.
- If the target has no hook file, no message to that effect is issued, and the current code generation execution hardware device, if left unspecified, defaults to MATLAB host computer for target device information. A message is displayed during code generation to indicate this default.

This second group of **Hardware Implementation** pane controls governs how hardware characteristics are handled in generated code. They do not appear unless the Real-Time Workshop product is installed. Their appearance varies depending on whether hardware configuration characteristics were previously specified for the model or not. If they were not, you see a button (as illustrated in the first of the two preceding figures) labeled **Configure current execution hardware device**. This button never again appears for this model once code has been generated and the model has been saved.

When you click the **Configure current execution hardware device** button, it is replaced by a check box labeled **None**. This box is selected by default, as shown in the following figure.



If you deselect this box, controls appear for that section that are identical to the controls for the **Embedded Hardware** section above, as shown in the next figure. In this figure, the TI-C6000 processor is selected.



Timing-Related Enhancements

- “Application Lifespan Option Optimizes Timer Data Storage” on page 118
- “Enabling the Rapid Simulation Target to Time Out” on page 118
- “New Asynchronous Block Library” on page 119

- “Automatic Slow-to-Fast and Fast-to-Slow Transition Detection for Rate Transition Block” on page 119
- “Automatic Insertion of Rate Transition Blocks” on page 120
- “Enhanced Absolute and Elapsed Time Computation” on page 120
- “Improved Single-Tasking Code Generation” on page 121

Application Lifespan Option Optimizes Timer Data Storage

The **Application lifespan (days)** field on the **Optimization** pane of the Configuration Parameters dialog box lets you specify how long an application, which contains blocks that depend on elapsed time, should be able to execute before timer overflow. Specifying it determines the word size used by timers in the generated code, and can lower RAM usage.

Application lifespan, when combined with the step size of each task, determinates data type of integer absolute time for each task, as follows:

- If your model does not require absolute time, this option affects neither simulation nor the generated code.
- If your model requires absolute time, this option optimizes the word size used for storing integer absolute time in generated code. This ensures that timers will not overflow within the lifespan you specify. If you set **Application lifespan (days)** to Inf, two uint32 words are used.
- If your model contains fixed-point blocks that require absolute time, this option affects both simulation and generated code.

Using 64 bits to store timing data enables models with a step size of 0.001 microsecond (10E-09 seconds) to run for more than 500 years, which would rarely be required. To run a model with a step size of one millisecond (0.001 seconds) for one day would require a 32-bit timer (but it could continue running for 49 days).

Application lifespan was an ERT-only option in prior releases.

Enabling the Rapid Simulation Target to Time Out

The Rapid Simulation (RSim) Real-Time Workshop target now has a timeout execution option, `-L n`. Use this option to enable the RSim executable to abort

if it is taking excessive time. This can happen, for example, in some models when zero crossings are frequent and minor step size is small.

For more information and an example, see “Setting a Clock Time Limit for a Rapid Simulation” in the Real-Time Workshop documentation.

New Asynchronous Block Library

A new VxWorks block library (vxlib1) allows you to model and generate code for asynchronous event handling, including servicing of hardware generated interrupts, maintenance of timers, asynchronous read and write operations, and spawning of asynchronous tasks under a real-time operating system (RTOS).

Although the blocks in the library target a particular RTOS (VxWorks Tornado), full source code and documentation are provided so that you can develop blocks supporting asynchronous event handling for your target RTOS.

The new VxWorks block library supports a superset of the functions of the older Interrupt Templates library. The new library is easier to use, since special Asynchronous Read and Write blocks are no longer required to handle rate transitions.

For descriptions of the VxWorks library blocks and information on gaining access to the library, see “Asynchronous Support” in the Real-Time Workshop documentation.

Compatibility Considerations. The older Interrupt Templates library (vxlib) is obsolete. It is provided only to allow models created prior to the Real-Time Workshop product V6.0 (R14) to continue to operate. If you have models that use vxlib blocks, The MathWorks recommends that you change them to use vxlib1 blocks.

Automatic Slow-to-Fast and Fast-to-Slow Transition Detection for Rate Transition Block

The Rate Transition block has been updated to automatically detect whether transitions must be slow-to-fast or fast-to-slow, and act appropriately. Accordingly, the Block Parameters dialog box for the block has been modified to include only the following four options:

- **Ensure data integrity during transfer**
- **Ensure deterministic data transfer**
- **Outport sample time**
- **Initial condition**

For more information, see “Sample Rate Transitions” in the Real-Time Workshop documentation.

Compatibility Consideration. Simulink automatically updates all Rate Transition blocks in a model with this enhancement when you save the model in V6 (R14).

Automatic Insertion of Rate Transition Blocks

When you set up a model to use a fixed-step solver for multitasking, Simulink now automatically inserts Rate Transition blocks between periodic tasks that run at different rates and transfer data. This feature does not apply to transitions to or from non-periodic (asynchronous) tasks. You can control whether Simulink inserts Rate Transition blocks automatically with the **Automatically handle data transfers between tasks** check box on the **Solver** pane of the Configuration Parameters dialog box.

Simulink configures the blocks that it inserts automatically to ensure both data integrity and deterministic data transfer. As mentioned above, this feature applies to multitasking models only. Rate Transition blocks that Simulink inserts automatically do not appear on the model’s block diagram. Nevertheless, they are implemented as semaphores or double buffers, depending on the constraints being observed, and affect simulation and code generation.

For more details, see “Automatic Rate Transition” in the Real-Time Workshop documentation.

Enhanced Absolute and Elapsed Time Computation

Certain blocks require the value of either *absolute* time (that is, the time from the start of program execution to the present time) or *elapsed* time (for example, the time elapsed between two trigger events). The Real-Time Workshop product now provides more efficient time computation services

to blocks that request absolute or elapsed time. These timer services are available to all targets that support the real-time model (`rtModel`) data structure. Improvements in the implementation of absolute and elapsed timers include

- Timers are implemented as unsigned integers in generated code.
- In multirate models, at most one timer is allocated per rate, on an as-needed basis. If no blocks executing at a given rate require a timer, no timer is allocated to that rate. This minimizes memory allocated for timers and significantly reduces overhead involved in maintaining timers.
- Allocation of elapsed time counters for use of blocks within triggered subsystems is minimized, further reducing memory usage and overhead.
- S-function and TLC APIs let you access timers for use in your S-functions, in both simulation and code generation.

For more information see “Timing Services” in the Real-Time Workshop documentation.

Improved Single-Tasking Code Generation

New efficiencies in code generation no longer require code generated for single-tasking models to test for sample hits in the base rate task. The code fragment below is an example of such a test in prior versions.

```
if (rtmIsSampleHit(S,0,tid)) { ...  
}
```

Since the base rate task always has a sample hit, such tests are not needed. Elimination of this test improves the runtime performance of the generated code.

GRT and ERT Target Unification

An important goal for both the Real-Time Workshop and Real-Time Workshop Embedded Coder products in V6.0 (R14) has been *target unification*. Target unification includes enhancements to the underlying technology and features of both products, such that:

- Both products use a common backend generated code format. This enhancement, termed *code format unification*, has a number of implications (see “Code Format Unification” on page 122).
- The set of features common to both products is expanded. Some features and efficiencies formerly exclusive to the Real-Time Workshop Embedded Coder product and the Embedded Real-Time (ERT) target are now generally available via the Generic Real-Time (GRT) target. Conversely, the Real-Time Workshop Embedded Coder software now supports some features that were previously available only via the GRT target (for example, support of continuous-time blocks and noninlined S-functions).

In general, the GRT and ERT targets have many more common features, but the ERT target offers additional controls for common features.

- Conversion from GRT-based targets to ERT-based targets is simplified.
- The ERT and GRT targets are fully backward-compatible with existing applications.

The following topics provide a high-level overview and comparison of feature enhancements and compatibility issues that result from target unification in the Real-Time Workshop product V6.0 (R14) and the Real-Time Workshop Embedded Coder product V4.0 (R14).

- “Code Format Unification” on page 122
- “Compatibility Considerations for GRT-Based Targets” on page 124
- “Real-Time Workshop and Real-Time Workshop® Embedded Coder Feature Set Comparison” on page 127
- “Symbol Formatting Options Replaced” on page 129

Code Format Unification

Before discussing *code format unification*, it is necessary to review the distinction between a target and a code format.

A target (such as the ERT target) is an environment for generating and building code intended for execution on a certain hardware or operating system platform. A target is defined at the top level by a system target file, which in turn invokes other target-specific files.

A code format (such as `Embedded-C` or `RealTime`) is one property of a target. The code format controls decisions made at several points in the code generation process. These include whether and how certain data structures are generated (for example, `SimStruct` or `rtModel`), whether or not static or dynamic memory allocation code is generated, and the calling interface used for generated model functions. In general, the `Embedded-C` code format is more efficient than the `RealTime` code format. `Embedded-C` code format provides more compact data structures, a simpler calling interface, and static memory allocation. These characteristics make the `Embedded-C` code format the preferred choice for production code generation.

In prior releases, only the ERT target and targets derived from the ERT target used the `Embedded-C` code format. Non-ERT targets used other code formats (for example, `RealTime` or `RealTimeMalloc`).

In V6.0 (R14, the GRT target uses the `Embedded-C` code format for backend code generation. This includes generation of both algorithmic model code and supervisory timing and task scheduling code. The GRT target (and derived targets) generates a `RealTime` code format wrapper around the `Embedded-C` code. This wrapper provides a calling interface that is backward-compatible with existing GRT-based custom targets. The wrapper calls are compatible with the main program module of the GRT target (`grt_main.c`). This use of wrapper calls incurs some calling overhead; the pure `Embedded-C` calling interface generated by the ERT target is more highly optimized.

The calling interface generated by the ERT target is described in “Data Structures, Code Modules, and Program Execution” of the Real-Time Workshop Embedded Coder documentation. The calling interface generated by the GRT target is described in “Program Architecture” of the Real-Time Workshop documentation.

Since the GRT target now uses the `Embedded-C` code format for backend code generation, many `Embedded-C` optimizations are available to all Real-Time Workshop product users. In general, the GRT and ERT targets have many more common features, but the ERT target offers additional controls for common features. The availability of features is now determined by licensing, rather than being tied to code format.

Code format unification simplifies the conversion of GRT-based custom targets to ERT-based targets. See “Compatibility Considerations for GRT-Based Targets” on page 124 for a description of target conversion issues.

Compatibility Considerations for GRT-Based Targets

If you have developed a GRT-based custom target, it is simple to make your target ERT-compatible. By doing so, you can take advantage of many efficiencies.

There are several approaches to ERT compatibility:

- If your installation does not include a Real-Time Workshop Embedded Coder license, you can convert a GRT-based target as described in “Converting Your Target to Use `rtModel`” on page 125. This enables your custom target to support all current GRT features, including backend Embedded-C code generation.
- You can create an ERT-based target, but continue to use your customized version of `grt_main.c` module. To do this, you can configure the ERT target to generate a GRT-compatible calling interface, as described in “Generating GRT Wrapper Code from the ERT Target” on page 126. This lets your target support all ERT features without changing your GRT-based runtime interface. This approach requires that your installation include a Real-Time Workshop Embedded Coder license.
- If your installation includes a Real-Time Workshop Embedded Coder license, you can reimplement your custom target as a completely ERT-based target, including use of an ERT generated main program. This approach lets your target support all ERT features, without the overhead caused by wrapper calls.

Note If you intend to use custom storage classes (CSCs) with a custom target, you must use an ERT target. See “Using Custom Storage Classes” in the Real-Time Workshop Embedded Coder documentation for information on CSCs.

For details on how GRT targets are made call-compatible with previous versions of the Real-Time Workshop product, see “The Real-Time Model Data Structure” in the Real-Time Workshop documentation.

Converting Your Target to Use `rtModel`. The real-time model data structure (`rtModel`) encapsulates model-specific information in a much more compact form than the `SimStruct`. Many ERT-related efficiencies depend on generation of `rtModel` rather than `SimStruct`, including:

- Integer absolute and elapsed timing services
- Independent timers for asynchronous tasks
- Generation of improved C API code for signal and parameter monitoring

To take advantage of such efficiencies, you must update your GRT-based target to use the `rtModel`, unless you already did so for V5.0 (R13). The conversion requires changes to your system target file, template makefile, and main program module.

To use `rtModel` instead of `SimStruct`, make the following changes to the system target file and template makefile:

- In the system target file, add the following global variable assignment:

```
%assign GenRTModel = TLC_TRUE
```

- In the template makefile, define the symbol `USE_RTMODEL`. See one of the GRT template makefiles for an example.

Make the following changes to your main program module (that is, your customized version of `grt_main.c`):

- Include `rtmodel.h` instead of `simstruc.h`.
- Since the `rtModel` data structure has a type that includes the model name, define the following macros at the top of main program file:

```
#define EXPAND_CONCAT(name1,name2) name1 ## name2
```

```
#define CONCAT(name1,name2) EXPAND_CONCAT(name1,name2)
```

```
#define RT_MODEL CONCAT(MODEL,_rtModel)
```

- Change the extern declaration for the function that creates and initializes the SimStruct to:

```
extern RT_MODEL *MODEL(void);
```

- Change the definitions of `rt_CreateIntegrationData` and `rt_UpdateContinuousStates` to be as shown in the Release 14 version of `grt_main.c`.
- Change all function prototypes to have the argument 'RT_MODEL' instead of the argument 'SimStruct'.
- The prototypes for the functions `rt_GetNextSampleHit`, `rt_UpdateDiscreteTaskSampleHits`, `rt_UpdateContinuousStates`, `rt_UpdateDiscreteEvents`, `rt_UpdateDiscreteTaskTime`, and `rt_InitTimingEngine` have changed. Change their names to use the prefix `rt_Sim` instead of `rt_` and then change the arguments you pass into them. See the V6.0 (R14) version of `grt_main.c` for the list of arguments passed into each function.
- Modify all macros that refer to `SimStruct` to now refer to `rtModel`. `SimStruct` macros begin with the prefix `ss`, whereas `rtModel` macros begin with the prefix `rtm`. For example, change `ssGetErrorStatus` to `rtmGetErrorStatus`.

Generating GRT Wrapper Code from the ERT Target. The Real-Time Workshop Embedded Coder software supports the **GRT compatible call interface** option. When you select this option, the Real-Time Workshop Embedded Coder build process generates model function calls that are compatible with the main program module of the GRT target (`grt_main.c`). These calls act as wrappers that interface to ERT (Embedded-C format) generated code.

This option provides a quick way to use ERT target features with a GRT-based custom target that has a main program module based on `grt_main.c`.

See “Code Generation Options and Optimizations” in the Real-Time Workshop Embedded Coder documentation for detailed information on the **GRT compatible call interface** option.

Real-Time Workshop and Real-Time Workshop Embedded Coder Feature Set Comparison

The approach you should take to achieve ERT compatibility depends on the features required by your custom target. The following table will help you decide whether or not you require Real-Time Workshop Embedded Coder licensed features.

For detailed information about these features, see the Real-Time Workshop and Real-Time Workshop Embedded Coder documentation.

Feature	Real-Time Workshop License	Real-Time Workshop Embedded Coder License
rtModel data structure	Full rtModel struct generated.	rtModel is optimized for the model. Suppression of error status field, data logging fields, and in the struct is optional.
Custom storage classes (CSCs)	Code generation ignores CSCs; objects assigned a CSC default to Auto storage class.	Code generation with CSCs supported.
HTML code generation report	Basic HTML code generation report.	Enhanced report with additional detail and hyperlinks to the model.
Symbol formatting	Symbols (for signals, parameters etc.) are generated in accordance with hard coded default.	Detailed control over generated symbols.
User-defined maximum identifier length for generated symbols	Supported	Supported
Generation of terminate function	Always generated.	Option to suppress terminate function.
Combined output/update function	Separate output/update functions are generated.	Option to generate combined output/update function.

Feature	Real-Time Workshop License	Real-Time Workshop Embedded Coder License
Optimized data initialization	Not available.	Options to suppress generation of unnecessary initialization code for zero-valued memory, I/O ports, etc.
Comments generation	Basic options to include or suppress comment generation.	Options to include Simulink block descriptions, Stateflow object descriptions, and Simulink data object descriptions in comments.
Module Packaging Features (MPF)	Not supported.	Extensive code customization features. See the Real-Time Workshop Embedded Coder documentation.
Target-optimized data types header file	Requires full <code>tmwtypes.h</code> header file.	Generates optimized <code>rtwtypes.h</code> header file, including only the necessary definitions required by the target.
User-defined types	User defined types default to base types in code generation.	User defined data type aliases are supported in code generation.
Simplified call interface	Non-ERT targets default to GRT interface.	ERT and ERT-based targets generate simplified interface.
Rate grouping	Not supported	Supported
Auto-generation of main program module	Not supported; static main program module provided.	Automated and customizable generation of main program module supported. Static main program also available.
MAT-file logging	No option to suppress MAT-file logging data structures.	Option to suppress MAT-file logging data structures.
Reusable (multi-instance) code generation with static memory allocation	Not supported.	Option to generate reusable code.

Feature	Real-Time Workshop License	Real-Time Workshop Embedded Coder License
Software constraint options	Support for floating point, complex, and nonfinite numbers always enabled.	Options to enable or disable support for floating point, complex, and nonfinite number.
Application life span	User-specified; determines most efficient word size for integer timers. Defaults to <code>inf</code> .	User-specified; determines most efficient word size for integer timers.
Software-in-the-loop (SIL) testing	Model reference simulation target can be used for SIL testing.	Additional SIL testing support via auto-generation of Simulink S-Function block.
ANSI C code generation	Supported	Supported
ISO-C code generation	Supported	Supported
GNU-C code generation	Supported	Supported
Generate scalar inlined parameters	Not supported	Supported
MAT-file variable name modifier	Supported	Supported
Data exchange: C API, External Mode, ASAP2	Supported	Supported

Symbol Formatting Options Replaced

This note discusses changes in the way that symbols are generated for

- Signals and parameters that have Auto storage class
- Subsystem function names that are not user-defined
- All Stateflow names

The following Real-Time Workshop model configuration options, all related to formatting generated symbols, have been removed from the Configuration

Parameters dialog box and replaced with a default symbol formatting specification.

- **Prefix model name to global identifiers**
- **Include System Hierarchy Number in Identifiers**
- **Include data type acronym in identifier**

The components of a generated symbol now include the root model name, followed by the name of the generating object (signal, parameter, state, and so on), followed by a unique *name mangling* string that is generated (if required) to resolve potential conflicts with other generated symbols.

The length of generated symbols is limited by the **Maximum identifier length** parameter specified on the **Real-Time Workshop>Symbols** pane of the **Configuration Parameters** dialog. The default length is 31 characters. When there is a potential name collision between two symbols, the Real-Time Workshop software generates a name mangling string. The string has the minimum number of characters required to avoid the collision. The Real-Time Workshop build process then inserts the other symbol components. If the **Maximum identifier length** is not large enough to accommodate full expansions of the other components, they are truncated.

Compatibility Considerations. To avoid truncation that can result from the new default symbol formatting specification, it is good practice to

- Avoid name collisions in general. One way to do this is to avoid using default block names (for example, Gain1, Gain2...) when there are many blocks of the same type in the model. Also, whenever possible, make subsystems atomic and reusable.
- Where possible, increase the **Maximum identifier length** to accommodate the length of the symbols you expect to generate.

Within a model that uses model referencing, there can be no collisions between the names of the constituent models. When generating code from a model that uses model referencing, the **Maximum identifier length** must be large enough to accommodate full the root model name and the name mangling string (if any). A code generation error occurs if **Maximum identifier length** is not large enough.

When a name conflict occurs between a symbol within the scope of a higher-level model and a symbol within the scope of a referenced model, the symbol from the referenced model is preserved. Name mangling is performed on the symbol from the higher-level model.

The Real-Time Workshop Embedded Coder software provides a **Symbol format** field that lets you control the formatting of generated symbols in much greater detail. See “Code Generation Options and Optimizations” in the Real-Time Workshop Embedded Coder documentation for more information.

Underscores No Longer Replace Spaces in Identifiers for Multi-Word Block Names

Prior to V6.0 (R14), the Real-Time Workshop product replaced each space in a multi-word block name with an underscore (_). For example, Actuator Model would be Actuator_Model. Starting in V6.0, the spaces in such names are removed rather than replaced. For example, the identifier for Actuator Model is generated as ActuatorModel.

Global Data Structure Identifiers for Targets Now Incorporate Model Name

Global data structures, such as rtB, rtP and rtY have new identifiers in ERT and GRT generated code. For GRT, these names now include the model name followed by _B, _P, _Y, and so on. (ERT targets provide you with flexible naming options as explained in “Symbol Formatting Options Replaced” on page 129). The construction of identifiers was changed to prevent name clashes when code for models containing Model blocks is generated and linked.

Compatibility Considerations

If you are interfacing external code to any Simulink global data, you might need to use the GRT compatible calling interface for ERT-based targets (see “Generating GRT Wrapper Code from the ERT Target” on page 126 for more information). The GRT interface enables you to access global data using the old-style identifiers via a set of macros that map old-style to new-style identifiers. See “Backwards Compatibility of Code Formats” in the Real-Time Workshop documentation for details.

Support for Simulink Configuration Set Feature

- “Support for New Simulink getActiveConfigSet Function” on page 132
- “New switchTarget Function” on page 132

Support for New Simulink getActiveConfigSet Function

A new function, `getActiveConfigSet`, provides safe access to option settings stored in the active configuration set. The function returns an object through which you can access properties of the model's active configuration set. The following example shows how to call `getActiveConfigSet` to turn the ERT **Single output/update function** off.

```
cs = getActiveConfigSet(model);
set_param(cs, 'CombineOutputUpdateFcns', 'off');
```

Compatibility Considerations. In prior releases, it was possible to access code generation options and other model parameters stored in the `rtwOptions` data structure directly, by using `get_param` and `set_param` calls. In the following code excerpt, for example, the value of the ERT **Single output/update function** option is changed from on to off.

```
options = get_param(model, 'RTWOptions');
strrep(options, 'CombineOutputUpdateFcns=1', 'CombineOutputUpdateFcns=0');
set_param(model, 'RTWOptions', options);
```

If you have written code that accesses the `rtwOptions` structure directly, as in the above example, you should update your code to use `getActiveConfigSet` instead. Due to changes in underlying data structures, code that accesses `rtwOptions` directly, as above, will no longer work correctly.

An alternative and more flexible method for automatic configuration of model options is available to Real-Time Workshop Embedded Coder users. See “Auto-Configuring Models for Code Generation” in the Real-Time Workshop Embedded Coder documentation for more information.

New switchTarget Function

In V6.0 (R14) Simulink models store model-wide parameters and target-specific data in *configuration sets*. Every configuration set contains a component that defines the structure of a particular target and the current

values of target options. Some of this information is loaded from a system target file when you select a target using the System Target File Browser. You can configure models to generate alternative target code by copying and modifying old or adding new configuration sets and browsing to select a new target. Subsequently, you can interactively select an active configuration from among these sets (only one configuration set can be active at a given time).


The Real-Time Workshop product has added a new function, `switchTarget`, to support configuration sets and enable you to automate target selection from scripts. Arguments that you pass to the function include a handle to the model's active configuration set and a string that specifies a system target file.

For more information, see “Selecting a System Target File Programmatically” in the Real-Time Workshop documentation.

Hardware Configuration Parameters

Compatibility Considerations

When you open a preexisting model that has not been saved using V6.0 (R14) of Simulink, and select **Hardware** in the Configuration Parameters dialog box, the following set of controls appears:



All but one of the parameters below the **Device type** menu are grayed out. This is because these characteristics have been preset for the default target

(32-bit Generic), as well as for several dozen known target processors that you can select from that menu.

In the event that none of the choices listed in the **Device Type** drop-down menu is appropriate for your intended hardware target, you can select **Custom**, and then set values for the hardware characteristics. Selecting any other option disables them. The hardware characteristics that you can specify are

- **Number of bits** — Text fields that specify the number of bits used to represent types **char**, **short**, **int**, and **long**. The values specified should be consistent with the word sizes as defined in the compiler's `limits.h` header file.
- **Byte ordering** — Specifies whether the target hardware uses **Big Endian** (most significant byte first) or **Little Endian** (least significant byte first) byte ordering. If left as **Unspecified**, the Real-Time Workshop build process generates code to determine the endianness of the target; this is the least efficient option.
- **Shift right on a signed integer as arithmetic shift** — ANSI C leaves the behavior of right shifts on negative integers as implementation dependent. Use this control to specify how the Real-Time Workshop software implements right shifts on signed integers in generated code.

The option is selected by default. If your C or C++ compiler handles right shifts as arithmetic shifts, this is the preferred setting.

- When the option is selected, the Real-Time Workshop software generates simple efficient code whenever the Simulink model performs arithmetic shifts on signed integers.
- When the option is cleared, the Real-Time Workshop software generates fully portable but less efficient code to implement right arithmetic shifts.

Enhancements and Changes that Affect Custom Targets


Defining and Displaying Custom Target Options

For release 14, extensive improvements and revisions have been made in the appearance and layout of code generation options and other target-specific options for Real-Time Workshop targets. If you have developed a custom

target, you should take advantage of the Model Explorer to present target options to end users.

Compatibility Considerations. To take advantage of the Model Explorer for presenting target options, you must modify your custom system target file. If you do not want to make the changes, a mechanism for using the old-style **Simulation Parameters** dialog is available for backwards compatibility.

The following figure shows an example of what users would see if you do not upgrade and the Embedded Target for Motorola HC12 target is selected.



Instead of one **Real-Time Workshop>Target** tab, this dialog has four: **ERT Code Generation options 1** through 3, **External mode options**, and **Code Warrior options** (not all are visible in the figure). Targets that have not been updated to use configuration sets will display similar dialogs. In addition, there is a **Launch old simprm dialog** button at the bottom of the dialog. Targets that use the **Simulation Parameters** dialog to handle callbacks will work without updating for Model Explorer only if the user uses

this button and then builds from the **Simulation Parameters** dialog. Note that configuration set dialogs can issue callbacks but handle them differently than did the **Simulation Parameters** dialog.

See the *Real-Time Workshop Embedded Coder Release Notes* for details.

New SelectCallback Function for System Target Files

The V6.0 (R14) API for system target file callbacks provides a new `SelectCallback` function for use in system target files. This function is associated with the target rather than with any of its individual options. If you implement a `SelectCallback` function for the target, it is triggered once, when the user selects the target via the System Target File Browser.

For details on using the `selectCallback` function, see “Supporting Optional Features” in the Real-Time Workshop Embedded Coder documentation.

Compatibility Considerations. If you have developed a custom target and you want it to be compatible with model referencing, you must implement a `SelectCallback` function to declare model reference compatibility. See “Compatibility Considerations for Custom Targets” on page 101 in the Real-Time Workshop documentation for an example.

Shared Utilities Directory and the Build Process

The shared utilities directory (`s1prj/target/_sharedutils`) typically stores generated utility code that is common between a top-level model and the models it references. You can also force the build process to use a shared utilities directory for a standalone model. See “Project Directory Structure for Model Reference Targets” in the Real-Time Workshop documentation for details.

Compatibility Considerations

If you want your target to support compilation of code generated in the shared utilities directory, several updates to your template makefile (TMF) are required. Note that support for the shared utilities directory is a necessary, but not sufficient, condition for supporting Model Reference builds. See “Compatibility Considerations for Custom Targets” on page 101 to learn about additional updates that are needed for supporting model reference builds.

The exact syntax of the changes can vary due to differences in the make utility and compiler/archive tools used by your target. The examples below are based on the GNU make utility. You can find the following updated TMF examples for GNU and Microsoft Visual C make utilities in the GRT and ERT target directories:

- GRT: *matlabroot/rtw/c/grt/*
 - *grt_lcc.tmf*
 - *grt_vc.tmf*
 - *grt_unix.tmf*
- ERT: *matlabroot/rtw/c/ert/*
 - *ert_lcc.tmf*
 - *ert_vc.tmf*
 - *ert_unix.tmf*

Use the GRT or ERT examples as a guide to the location, within the TMF, of the changes and additions described below.

Note The ERT-based TMFs contain extra code to handle generation of ERT S-functions and Model Reference simulation targets. Your target does not need to handle these cases.

Make the following changes to your TMF to support the shared utilities directory:

- 1 Add the following make variables and tokens to be expanded when the makefile is generated:

```

SHARED_SRC      = |>SHARED_SRC<|
SHARED_SRC_DIR  = |>SHARED_SRC_DIR<|
SHARED_BIN_DIR  = |>SHARED_BIN_DIR<|
SHARED_LIB      = |>SHARED_LIB<|

```

SHARED_SRC specifies the shared utilities directory location and the source files in it. A typical expansion in a makefile is

```
SHARED_SRC      = ../slprj/ert/_sharedutils/*.c
```

SHARED_LIB specifies the library file built from the shared source files, as in the following expansion.

```
SHARED_LIB      = ../slprj/ert/_sharedutils/rtwshared.lib
```

SHARED_SRC_DIR and SHARED_BIN_DIR allow specification of separate directories for shared source files and the library compiled from the source files. In the current release, all TMFs actually use the same path, as in the following expansions.

```
SHARED_SRC_DIR = ../slprj/ert/_sharedutils
SHARED_BIN_DIR = ../slprj/ert/_sharedutils
```

- 2 Set the SHARED_INCLUDES variable according to whether shared utilities are in use. Then append it to the overall INCLUDES variable.

```
SHARED_INCLUDES =
ifneq ($(SHARED_SRC_DIR),)
SHARED_INCLUDES = -I$(SHARED_SRC_DIR)
endif
INCLUDES = -I. $(MATLAB_INCLUDES) $(ADD_INCLUDES) \
           $(USER_INCLUDES) $(SHARED_INCLUDES)
```

- 3 Update the SHARED_SRC variable to list all shared files explicitly.

```
SHARED_SRC := $(wildcard $(SHARED_SRC))
```

- 4 Create a SHARED_OBJS variable based on SHARED_SRC.

```
SHARED_OBJS = $(addsuffix .o, $(basename $(SHARED_SRC)))
```

- 5 Create an OPTS (options) variable for compilation of shared utilities.

```
SHARED_OUTPUT_OPTS = -o $@
```

- 6 Provide a rule to compile the shared utility source files.

```
$(SHARED_OBJS) : $(SHARED_BIN_DIR)/%.o : $(SHARED_SRC_DIR)/%.c
$(CC) -c $(CFLAGS) $(SHARED_OUTPUT_OPTS) $<
```

- 7** Provide a rule to create a library of the shared utilities. The following example is UNIX-based.

```
$(SHARED_LIB) : $(SHARED_OBJS)
    @echo "### Creating $@"
    ar r $@ $(SHARED_OBJS)
    @echo "### Created $@"
```

- 8** Add SHARED_LIB to the rule that creates the final executable.

```
$(PROGRAM) : $(OBJS) $(LIBS) $(SHARED_LIB)
$(LD) $(LDFLAGS) -o $@ $(LINK_OBJS) $(LIBS) $(SHARED_LIB)
$(SYSLIBS)
@echo "### Created executable: $(MODEL)"
```

- 9** Remove any explicit reference to `rt_nonfinite.c` from your TMF. For example. change

```
ADD_SRCS = $(RTWLOG) rt_nonfinite.c
```

to

```
ADD_SRCS = $(RTWLOG)
```

Note If your target interfaces to a development environment that is not makefile based, you must make equivalent changes to provide the needed information to your target compilation environment.

Tornado Target Requires Macro in Template Make File

Tornado 2.2.1 installs standard header files in an include directory under the target compiler target directory. For example, if you are targeting the Motorola 68k processor for VxWorks with the GCC 2.96 compiler, Tornado installs the header files at the following location:

```
WIND_BASE/host/WIND_HOST_TYPE/lib/gcc-lib/m68k-wrs-vxworks
/gcc-2.96/include
```

If you are using a version of Tornado lower than 2.2.1, leave the macro commented out.

Compatibility Considerations

To use Tornado 2.2.1 or higher with the Tornado (VxWorks) Real-Time Target, `tornado.tlc`, you must enable a macro in template makefile `tornado.tmf` as follows:

- 1 Open `matlabroot/rtw/c/tornado/tornado.tmf`.
- 2 Search for `TORNADO_TARGET_COMPILER_INCLUDES`.
- 3 Uncomment the macro `TORNADO_TARGET_COMPILER_INCLUDES` and set it to the include directory that contains the Tornado standard header files.

Given the path shown above, you would set the macro as follows:

```
TORNADO_TARGET_COMPILER_INCLUDES =
$(WIND_BASE)/host/$(WIND_HOST_TYPE)/lib/gcc-lib/m68k-wrs-v
xworks/gcc-2.96/include
```

Although this example shows the macro definition wrapped, you should include it on a single line.

Custom Storage Classes Can No Longer Be Used with GRT Targets

In prior releases, it was possible to use custom storage classes with the GRT target if a Real-Time Workshop Embedded Coder license was available. In V6.0 (R14), you can no longer use custom storage classes when you generate code for GRT-based targets.

For information on how GRT and ERT targets now compare, see “Global Data Structure Identifiers for Targets Now Incorporate Model Name” on page 131. See “Code Generation Options and Optimizations” in the Real-Time Workshop Embedded Coder documentation for detailed information on the **GRT compatible call interface** option.

Compatibility Considerations

If you have a Real-Time Workshop Embedded Coder license and want to build a model that uses custom storage classes with the GRT target, you should instead use ERT Target, and enable the **GRT compatible call interface** option. This option appears on the **Real-Time Workshop>Interface** pane

of the Configuration Parameters dialog box. When you use this option, the Real-Time Workshop Embedded Coder software generates GRT-compatible code that can include custom storage classes.

Target Language Compiler Enhancements and Changes

- “ISSLPRMREF TLC Built-In Supports Parameter Sharing with Simulink” on page 141
- “New Argument for TLC GENERATE_FORMATTED_VALUE Built-In Function” on page 141
- “Accessing the Number of Sample Times from TLC for Custom Targets” on page 142
- “TLCFILES Built-In Now Returns Full Path to Model File Rather Than Relative Path” on page 142

ISSLPRMREF TLC Built-In Supports Parameter Sharing with Simulink

To support parameter sharing with Simulink, a new built-in function (ISSLPRMREF) has been added to the Target Language Compiler. It returns a Boolean value indicating whether its argument is a reference to a Simulink parameter or not. Using this function can save memory and time during code generation. Here is an example:

```
%if !ISSLPRMREF(param.Value)
    %assign param.Value = CAST("Real", param.Value)
%endif
```

New Argument for TLC GENERATE_FORMATTED_VALUE Built-In Function

The GENERATE_FORMATTED_VALUE built-in function has a new optional third argument. The syntax for the function is now

```
GENERATE_FORMATTED_VALUE(expr, string, expand)
```

The third argument is a Boolean, which when TRUE, causes `expr` to be expanded into raw text before being output. `expand=TRUE` uses much more memory than the default (FALSE). Set `expand=TRUE` only if the parameter text needs to be processed for some reason before being written to disk.

Accessing the Number of Sample Times from TLC for Custom Targets

In previous release, you could directly access an undocumented TLC variable, `NumSampleTimes`, which held the number of periodic (synchronous) sample times. In the current release, the variable that holds the number of periodic sample times is called `NumSynchronousSampleTimes`. In addition, there are two new variables, `NumAsynchronousSampleTimes` and `NumVariableSampleTimes`. The total number of sample times in a model is given by:

$$\text{NumSampleTimes} = \text{NumSynchronousSampleTimes} + \text{NumAsynchronousSampleTimes} + \text{NumVariableSampleTimes}$$

Compatibility Considerations. Do not use `NumSampleTimes`. Instead, call TLC library functions, as follows:

- `LibNumDiscreteSampleTimes()` to access `NumSynchronousSampleTimes`
- `LibNumAsynchronousSampleTimes()` to access `NumAsynchronousSampleTimes`

TLCFILES Built-In Now Returns Full Path to Model File Rather Than Relative Path

A change in TLC invocation now specifies a full path to model files rather than a relative path.

Compatibility Considerations. This change creates backwards incompatibility in some custom targets.

When migrating V5.0 (R13) custom targets to V6.0 (R14), check for and adjust usage of the TLC function `TLCFILES` to determine context, such as the path to the model file, as necessary.

Documentation Enhancements

- *Real-Time Workshop Getting Started Guide* has been fully updated and includes a new tutorial on generating code for referenced models.
- *Real-Time Workshop User's Guide* is updated, and includes most of the information on new features described in this chapter.
- *Real-Time Workshop Target Language Compiler* has been updated. This document no longer includes an appendix describing all the records that might be encountered in a *model.rtw* file.

Version 5.2 (R13SP2) Real-Time Workshop Software

This table summarizes what's new in V5.2 (R13SP2):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
No	No	Fixed bugs	V5.2 product documentation

Version 5.1.1 (R13SP1+) Real-Time Workshop Software

This table summarizes what's new in V5.1.1 (R13SP1+):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	Fixed bugs	No

New features and changes introduced in this version are

- “New -dr Command Line Switch in TLC Detects Cyclic Record Creation” on page 145
- “Error Resulting from Inaccessible Signal Reporting No Longer Reported” on page 146

New -dr Command Line Switch in TLC Detects Cyclic Record Creation

The -dr command line option enables the Target Language Compiler to detect at run time when cyclic records are created and to produce a diagnostic message.

Cyclic records are problematic because they cause memory leaks in TLC. A cyclic record is one which ends up pointing to itself. They can be constructed only manually, as in the following example:

```
%createrecord x { }    %% create an empty record x
%createrecord y { }    %% create an empty record y

%addtorecord x field y %% add a field to x which points to y
%addtorecord y field x %% add a field to y which points to x
```

At this point, a cyclic record exists — `x.field.field == x`.

As this feature significantly slows Target Language Compiler performance, it is off by default.

Error Resulting from Inaccessible Signal Reporting No Longer Reported

Compatibility Considerations

In previous releases, Simulink and the Real-Time Workshop software reported an error whenever a Floating Scope or a user-written S-function tried to access an inaccessible signal during simulation or code generation. In this release, Simulink displays only a warning if you use the `sim` command to start the simulation. The Real-Time Workshop software generates neither a warning nor an error message.

Version 5.1 (R13SP1) Real-Time Workshop Software

This table summarizes what's new in V5.1 (R13SP1):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
No	No	Fixed bugs	No

Version 5.0.1 (R13+) Real-Time Workshop Software

This table summarizes what's new in V5.0.1 (R13+):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	No	Fixed bugs	No

New features and changes introduced in this version are

- “Expanded Hook File Options” on page 148
- “Hook Files for Customizing Make Commands” on page 150

Expanded Hook File Options

This update adds new options for specifying target characteristics via hook files.

During the Real-Time Workshop build process, the software checks for the existence of *target_rtw_info_hook.m*, where *target* is the base file name of the active system target file. For example, if your system target file is *grt.tlc*, then the hook file name is *grt_rtw_info_hook.m*. If the hook file is present (that is, is on the MATLAB path), the target specific information is extracted via the API found in this file. Otherwise, the host computer is the assumed target.

Three hook file keyword options have been added since V5.0 (R13):

- `TypeEmulationWarnSuppressLevel`
Suppresses warnings about emulation of word sizes. The default value is 0, which gives full warnings. This is the preferred setting when generating code for the production target. Increasing the value gives less warnings. When generating code for a rapid prototyping system, emulation may not be a concern and a suppression level of 2 may be desirable.
- `PreprocMaxBitsSint`:

Specifies limitations of the target C preprocessor to do math with signed integers. Use this option to prevent errors in the preprocessor phase.

As an example, suppose the target had 64-bit longs. Porting the generated code to a machine that does not have 64-bit longs can lead to errors in the processing of integer data types. To prevent these errors, a check is included in the generated code.

```
#if ( LONG_MAX != (0x7FFFFFFFFFFFFFFFL) )
#error Code was generated for compiler with different sized
longs.
#endif
```

This code requires the preprocessor to compare signed 64-bit integers. Some preprocessors have bugs that cause such comparisons to yield incorrect results. The preprocessor math may only be fully correct for say 32-bit signed integers. To specify, this `PreprocMaxBitsSint` would be set to 32. Generating the code with this setting causes problematic size checks to be skipped.

```
#if 0
/*
Skip this size verification because of preprocessor
limitation
*/
#if ( LONG_MAX != (0x7FFFFFFFFFFFFFFFL) )
#error Code was generated for compiler with different sized
longs.
#endif
#endif
```

- `PreprocMaxBitsUint`

Specifies limitations of the target C preprocessor to do math with unsigned integers. This is just like `PreprocMaxBitsSint` except that it pertains to unsigned integer operations such as

```
#if ( ULONG_MAX != (0xFFFFFFFFFFFFFFFFUL) )
```

If you are not certain about the proper settings for your target, you can get more details by typing `rtwtargetsettings` in the MATLAB Command Window.

Hook Files for Customizing Make Commands

Custom targets may require a target-specific hook file to generate an appropriate make command when a nondefault compiler is used. Such M-files should be located on the MATLAB path and be named *target_wrap_make_cmd_hook.m* (for example, *MPC555pil_wrap_make_cmd_hook.m* for the MPC555 PIL target). When such a file exists, and returns an appropriate make command, the Real-Time Workshop software overrides its default (for example, Lcc) batch file wrapping code. For an example make command hook file, see *matlabroot/toolbox/rtw/rtw/wrap_make_cmd.m*. Such hook files are distinct from the target-specific hook files used to describe hardware characteristics (see “Expanded Hook File Options” on page 148).

Version 5.0 (R13) Real-Time Workshop Software

This table summarizes what's new in V5.0 (R13):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	Fixed bugs	No

New features and changes introduced in this version are organized by these topics:

- “Compiler Support Enhancements” on page 152
- “Model Configuration Features and Enhancements” on page 152
- “Code Generation Infrastructure Enhancements” on page 158
- “Block Enhancements” on page 167
- “Rapid Simulation Target Enhancement” on page 169
- “External Mode Enhancements” on page 169
- “Simulink Data Object Enhancements” on page 170
- “model.rtw Changes” on page 170
- “Generate HTML Report Option Available for Additional Targets” on page 171
- “Efficiency of Code Generated for GRT and GRT-Malloc Targets Improved” on page 172
- “Logging Code Moved to the Real-Time Workshop Library” on page 172
- “Custom Code Blocks Moved from Simulink Library” on page 173
- “Target Language Compiler Changes” on page 173
- “Documentation Enhancements” on page 174

- “Fixed Bugs” on page 174
- “Limitations for HP and IBM Platforms” on page 180

Compiler Support Enhancements

- “Expanded Support for Borland C Compilers” on page 152
- “Lcc Now Links Libraries in Directory sys/lcc/lib” on page 152

Expanded Support for Borland C Compilers

The Real-Time Workshop product supports Version 5.6 of the Borland C compiler.

In addition, V5.0 (R13) reinstates support for Borland Version 5.2 "out-of-the-box" for all targets, except when Real-Time Workshop generates importing S-functions. In such instances, designate the build directory where the S-function may be found via the `make_rtw` parameter `USER_INCLUDES`. For example, suppose you had generated S-function target code for model `modelA.mdl` in build directory `D:\modelA_sfcn_rtw` and were using that S-function in model `modelB.mdl`. In `modelB.mdl`, the **Make command** field of your Target configuration category should define `USER_INCLUDES` as follows:

```
make_rtw "USER_INCLUDES=-ID:\modelA_sfcn_rtw"
```

Lcc Now Links Libraries in Directory sys/lcc/lib

Template makefiles have been updated to include linking against `sys/lcc/lib`.


Model Configuration Features and Enhancements

- “Diagnostics Pane Items Classified into Logical Groups” on page 153
- “Comments Not Generated for Reduced Blocks When "Show eliminated statements" Is Off” on page 153
- “New General Code Appearance Options” on page 154

- “Identifier Construction for Generated Code Has Been Simplified” on page 156
- “GUI Control over Behavior of Assertion Blocks in Generated Code” on page 157
- “GUI Control Over TLC %assert Directive Evaluation” on page 157

Diagnostics Pane Items Classified into Logical Groups

To make selecting diagnostics easier, the **Diagnostics** entries on the **Simulation Parameters** dialog box have been reorganized according to functionality, and alphabetically within each group, as shown in the next figure.




Comments Not Generated for Reduced Blocks When "Show eliminated statements" Is Off

The **Show eliminated statements** option (in the Real-Time Workshop General code generation options category) is now off by default. As long as it remains off, the Real-Time Workshop software no longer generates comments referring to blocks that have been removed from the model via block reduction optimization.

Compatibility Considerations. If you want the Real-Time Workshop software to generate comments for blocks that are removed due for block reduction optimization, select the **Show eliminated statements** option.

New General Code Appearance Options

A new section has been added to the **Real-Time Workshop** pane of the Simulation Parameters dialog box, named **General code appearance options**. The new section groups four new code formatting options to two existing options. The **General code appearance** appear as shown in the next figure.



The four new options are

Option	Description
Maximum identifier length	Allows you to limit the number of characters in function, type definition, and variable names. The default is 31 characters, but the Real-Time Workshop software imposes no upper limit.

Option	Description
Include data type acronym in identifier	Perpend acronyms such as <code>i32</code> (for long integers) to signal and work vector identifiers to make code more readable. The default is not to include data type acronyms in identifiers.
Include system hierarchy number in identifiers	Adds prefixes <code>s#_</code> , where <code>#</code> is a unique integer subsystem index, to identifiers declared in that subsystem. This enhances traceability of code, for example via the <code>hilite_system<'S#'</code> command. The default is not to include a system hierarchy index in identifiers.
Prefix model name to global identifiers	Prefixes subsystem function names with the name of the model (<code>model_</code>). The model name is also prefixed to the names of functions and data structures at the model level, when appropriate to the code format. This is useful when you need to compile and link code from two or more models into a single executable, as it avoids potential name clashes. This option is on by default.
Generate scalar inline parameters as:	<p>Controls the code style for inlined parameters. You can set this option to <code>literals</code> or <code>macros</code>. When constant parameters are inlined and declared not tunable, the following code generation options are available:</p> <ul style="list-style-type: none"> • Vector parameters were formerly stored as constant parameters in <code>rtP</code> vectors. Now they are declared as constant vectors of appropriate type, independent of <code>rtP</code>. • Scalar parameters were formerly inlined as literals. In addition to this approach, users now have the option to have scalar

Option	Description
	<p>parameters expressed as <code>#define</code> macro definitions.</p> <p>The default is to generate scalar inline parameters as literals.</p> <p>Note: S-functions can mark a run-time parameter as being constant to guarantee that it never ends up in the <code>rtP</code> data structure. Use <code>ssSetConstRunTimeParamInfo</code> in the S-function to register a constant runtime parameter.</p>
Generate comments	<p>An existing global option moved from the General code generation options (cont) category to this one. As in the prior release, by default Generate comments is on.</p>

Identifier Construction for Generated Code Has Been Simplified

The methods the Real-Time Workshop software uses to construct identifiers for variables and functions have been enhanced to make identifiers more understandable and more customizable. As a result of these enhancements

- Changes to sections of the model do not cause identifiers elsewhere to change.
- Reused function input arguments now derive their name from the inport block.
- Subsystem function names can be prefixed by the model name to prevent link errors due to name conflicts.
- You can specify a maximum identifier length (can be > 31 characters).
- A new option exists to include a data type acronym in identifiers.
- Use of `_a`, `_b`, ... postfixes to identifiers to prevent name clashes has been dramatically reduced.

GUI Control over Behavior of Assertion Blocks in Generated Code

The **Advanced** pane of the Simulation Parameters dialog box provides a new **Model Verification block control** popup menu you can use to specify whether model verification blocks such as Assert, Check Static Gap, and related range check blocks will be enabled, not enabled, or default to their local settings. This popup menu has the same effect on Real-Time Workshop generated code as it does on simulation behavior, and also may be customized.

For Assertion blocks that are not disabled, the generated code for a model includes one of the following statements at appropriate locations, depending on the block's input signal type (Boolean, real, or integer, respectively).

```
utAssert(input_signal);
utAssert(input_signal != 0.0);
utAssert(input_signal != 0);
```

By default `utAssert` is a non-option in generated code. For assertions to abort execution you must enable them by including a parameter in the `make_rtw` command. Specify the **Make command** field on the Target configuration category pane as follows:

```
make_rtw OPTS="-DDOASSERTS"
```

If you want triggered assertions to not abort execution and instead to print out the assertion statement, use the following `make_rtw` variant:

```
make_rtw OPTS="-DDOASSERTS -DPRINT_ASSERTS"
```

Finally, when running a model in accelerator mode, Simulink calls back to itself to execute assertion blocks instead of using generated code. Thus a user-defined callback is still called when assertions fail.

GUI Control Over TLC %assert Directive Evaluation

Prior versions required you to specify the `-da` Target Language Compiler command switch for TLC `%assert` directives to be evaluated. Now you can more conveniently trigger `%assert` code by selecting the **Enable TLC Assertions** check box on the **TLC debugging** section of the **Real-Time Workshop** dialog. The default state is for asserts not to be evaluated. You can also control assertion handling from the MATLAB command window.

To set or unset assertion handling, use the following command. The option is off by default.

```
set_param(model, 'TLCAssertion', 'on|off')
```

To see the current setting, use the command

```
get_param(model, 'TLCAssertion')
```

Code Generation Infrastructure Enhancements


- “Code for Nonvirtual Subsystems Is Now Reusable” on page 158
- “Packaging of Generated Code Files Simplified” on page 160
- “Different Required Files for S-Function Deployment” on page 162
- “Most Targets Use rtModel Instead of Root SimStruct” on page 163
- “Hook Files Required for Communicating Target-specific Word Characteristics” on page 165
- “Code Generation Unified for Real-Time Workshop and Stateflow Products” on page 166
- “Conditional Input Branch Execution Optimization” on page 166

Code for Nonvirtual Subsystems Is Now Reusable

The Real-Time Workshop software V5.0 (R13) introduces the ability to reuse code generated for nonvirtual subsystems. In prior releases, the Real-Time Workshop software generated a separate block of code for each nonvirtual subsystem. In some circumstances — for example, when you use a library block multiple times in the same fashion — it is now possible to generate a single shared function for the block and call that function multiple times. Consolidating code in this fashion can significantly improve the size and efficiency of generated code.

To implement code reuse, the Real-Time Workshop build process must pass in appropriate data elements (as function arguments) for each caller of a reused subsystem. Code generated by the Real-Time Workshop software V5.0 (R13) enables such arguments for functions generated for nonvirtual subsystems.

You enable code reuse through the **Subsystem parameters** dialog when both **Treat as atomic unit** and **Reusable function** from the **RTW system code** pull-down menu are selected, as illustrated in the next figure.



Reusable code will also be generated, when feasible, when you set **RTW system code** to **Auto**. Then, if only one instance of the subsystem exists, it will be inlined; otherwise a reusable function will be generated if other characteristics of the model allow this.

Certain conditions may make it impossible to reuse code, causing the Real-Time Workshop build process to revert to another **RTW system code** option even though you specify **Reusable function** or **Auto**. When you specify **Reusable function** and reuse is not possible, the result is a function without arguments. When you specify **Auto** and reuse is not possible, the Real-Time Workshop build process inlines the subsystem's code (or in special cases, creates a function without arguments). Diagnostics are available in the HTML code generation report (if enabled, see "Generate HTML Report Option Available for Additional Targets" on page 171) to help identify the reasons why reuse is not occurring in particular instances. In addition to providing these exception diagnostics, the HTML report's **Subsystems** section also

maps each noninlined subsystem in the model to functions or reused functions in the generated code.

Requirements for Generating Reusable Code from Stateflow Charts.

To generate reusable code from a Stateflow chart, or from a subsystem containing a Stateflow chart, all of the following conditions must be met:

- The chart (or subsystem containing the chart) must be a library block (see “Working with Block Libraries” in the Simulink documentation).
- Data in the chart must not be initialized from workspace. The data property **Initialize from workspace** should be off.
- The chart must not output a function call.

See “Nonvirtual Subsystem Code Generation” in the Real Time Workshop documentation for more details.

Compatibility Considerations. The Real-Time Workshop software V5.0 (R13) alters aspects of generated code to support code reuse for nonvirtual subsystems. As explained above, you have the ability to select or override this feature, as well as to specify function and file names from the graphical user interface.

Packaging of Generated Code Files Simplified

The packaging of generated code into .c and .h files has been simplified. The following table summarizes the structure of source code generated by the Real-Time Workshop software. All code modules described are written to the build directory.

Note The Real-Time Workshop Embedded Coder file packaging differs slightly (but significantly) from the file packaging described here. See “Code Modules” in the Real-Time Workshop Embedded Coder User’s Guide for more information.

File	Description
<i>model.c</i>	Contains entry points for all code implementing the model algorithm (MdlStart, MdlOutputs, MdlUpdate, MdlInitializeSizes, MdlInitializeSampleTimes). Also contains model registration code.
<i>model_private.h</i>	Contains local defines and local data that are required by the model and subsystems. This file is included by <i>subsystem.c</i> files in the model. You do not need to include <i>model_private.h</i> when interfacing handwritten code to a model.
<i>model.h</i>	Defines model data structures and a public interface to the model entry points and data structures. Also provides an interface to the real-time model data structure (<i>model_rtM</i>) via access macros. <i>model.h</i> is included by <i>subsystem.c</i> files in the model. If you are interfacing your handwritten code to generated code for one or more models, you should include <i>model.h</i> for each model to which you want to interface.
<i>model_data.c</i> (conditional)	<i>model_data.c</i> is conditionally generated. It contains the declarations for the parameters data structure and the constant block I/O data structure. If these data structures are not used in the model, <i>model_data.c</i> is not generated. Note that these structures are declared extern in <i>model.h</i> .
<i>model_types.h</i>	Provides forward declarations for the real-time model data structure and the parameters data structure. These may be needed by function declarations of reusable functions. <i>model_types.h</i> is included by all <i>subsystem.h</i> files in the model.

File	Description
<code>rtmodel.h</code>	Contains <code>#include</code> directives required by static main program modules such as <code>grt_main.c</code> and <code>grt_malloc_main.c</code> . Since these modules are not created at code generation time, they include <code>rt_model.h</code> to access model-specific data structures and entry points. If you create your own main program module, take care to include <code>rtmodel.h</code> .
<code>model_pt.c</code> (optional)	Provides data structures that enable a running program to access model parameters without use of external mode.
<code>model_bio.c</code> (optional)	Provides data structures that enable your code to access block outputs.

Compatibility Considerations. If you have interfaced handwritten code to code generated by previous releases of the Real-Time Workshop software, you might need to remove dependencies on header files that are no longer generated. Use `#includemodel.h` directives, and remove `#include` directives that refer to any of the following:

Old Filename	New Filenames
<code>model_common.h</code>	<code>model_types.h</code> and <code>model_private.h</code>
<code>model_export.h</code>	<code>model.h</code>
<code>model_prm.h</code>	<code>model_data.c</code>
<code>model_reg.h</code>	<code>model.c</code>

Different Required Files for S-Function Deployment

In previous releases, the files required for deploying an S-function block that you generated using the S-function target were the following:

- For S-function inclusion in other models for simulation, the binary MEX-file object `subsys_sf.mexext`, where `subsys` is the subsystem name

and *mexext* is a platform-dependent MEX-file extension. (For example, `SourceSubsys_sf.dll`.)

- For S-function inclusion in other models for code generation, *subsys_sf.c* (the stub file), *subsys_sf.mexext*, and subdirectory *subsys_sfcn_rtw* with at least the following files:
 - *subsys_sf.c*
 - *subsys_sf.h*
 - *subsys_sf_common.h*
 - *subsys_sf_export.h*
 - *subsys_sf_prm.h*
 - *subsys_sf_reg.h*
 - *subsys_sid.h*

Beginning in the Real-Time Workshop software V5.0 (R13) , due to the packaging improvements described in “Packaging of Generated Code Files Simplified” on page 160, different files are required for deploying your S-function block. For details, see “Required Files for S-Function Deployment”.

Compatibility Considerations. To deploy your S-function blocks for inclusion in models created in R13 or a later release, you should regenerate the S-function blocks using the same release that created the models, and deploy the S-function blocks using the files described in “Required Files for S-Function Deployment”.

Most Targets Use `rtModel` Instead of `Root SimStruct`

The GRT, GRT-Malloc, ERT, and Tornado targets now use the `rtModel` data structure to store information about the root model.

Compatibility Considerations. In prior releases, the information about the root models was stored in the data structure `SimStruct`. Since the `SimStruct` data structure was also used by noninlined S-functions, it contained a number of S-function fields that were not needed to represent root model information. The new `rtModel` structure is lightweight and eliminates the unused fields in representing the root model. Fields in the `rtModel` capture model-wide information pertaining to timing, solvers, logging, model data (such as block I/O and `DWork` parameters), and so on. To generate code for the ERT target, the `rtModel` data structure is further pruned to contain only those fields that are relevant to the model under consideration.

If you have previously customized GRT, GRT-Malloc, or Tornado targets, upgrade each customized target to use the `rtModel` instead of `SimStruct`.

To upgrade a target to use the `rtModel` instead of the `SimStruct`:

- Include `rtmodel.h` instead of `simstruc.h` at the top.
- Since the `rtModel` data structure has a type that includes the model name, you need to include the following lines at the top of the file:

```
#define EXPAND_CONCAT(name1,name2) name1 ## name2
#define CONCAT(name1,name2) EXPAND_CONCAT(name1,name2)
#define RT_MODEL CONCAT(MODEL,_rtModel)
```

- Change the extern declaration for the function that creates and initializes the `SimStruct` to be:

```
extern RT_MODEL *MODEL(void);
```

- Change the definitions of `rt_CreateIntegrationData` and `rt_UpdateContinuousStates` to be as shown in the Release 13 version of `grt_main.c` (or `grt_malloc_main.c`).
- Change all function prototypes to have the argument '`RT_MODEL`' instead of the argument '`SimStruct`'.
- Change the names of the following functions such that they use the prefix `rt_Sim` instead of `rt_` and then change the arguments you pass into them.

```
rt_GetNextSampleHit
rt_UpdateDiscreteTaskSampleHits
```



```

rt_UpdateContinuousStates
rt_UpdateDiscreteEvents
rt_UpdateDiscreteTaskTime
rt_InitTimingEngine

```

See `grt_main.c` (or `grt_malloc_main.c`) for the list of arguments that need to be passed into each function.

- Modify macros that refer to the `SimStruct` to now refer to the `rtModel`. Examples of these modifications include changing
 - `ssGetErrorStatus` to `rtmGetErrorStatus`
 - `ssGetSampleTime` to `rtmGetSampleTime`
 - `ssGetSampleHitPtr` to `rtmGetSampleHitPtr`
 - `ssGetStopRequested` to `rtmGetStopRequested`
 - `ssGetTFinal` to `rtmGetTFinal`
 - `ssGetT` to `rtmGetT`

In addition to the changes to the main C files, change the target TLC file and the template make files.

- In your template make file, define the symbol `USE_RTMODEL`. See one of the GRT or GRT-Malloc template makefiles for an example.
- In your target TLC file, add the following global variable assignment:

```
%assign GenRTModel = TLC_TRUE
```

Hook Files Required for Communicating Target-specific Word Characteristics

You must now supply a target hook file (M-file) to specify target hardware characteristics, such as word sizes and overflow behavior.

Compatibility Considerations. To communicate details about target hardware characteristics, you must now supply an M-file named *target_rtw_info_hook.m*. Each system target file needs to implement a hook file. For GRT (*grt.tlc*), for example, you must name the file *grt_rtw_info_hook.m*, and the file needs to be on the MATLAB path. If the hook file is not provided, the Real-Time Workshop software uses default values based on the host's characteristics, which may not be appropriate. For an example, see *toolbox/rtw/rtwdemos/example_rtw_info_hook.m*. In addition, note that the TLC directive `%assign DSP = 1` no longer has any effect. You need to provide a hook file instead.

Code Generation Unified for Real-Time Workshop and Stateflow Products

The Real-Time Workshop build process now generates code for models that include Stateflow charts in a single set of output files.

Compatibility Considerations. In earlier releases, the Real-Time Workshop build process wrote code generated from Stateflow charts to source code files distinct from the source code files (such as *model.c*, *model.h*, etc.) generated from the rest of a model.

Now, by default, the Stateflow software no longer generates any separate files from the Real-Time Workshop software. In addition, Stateflow generated code is seamlessly integrated with other generated code. For example, all Stateflow initialization code is now inlined.

You can override the default and instruct the Real-Time Workshop build process to generate separate functions, within separate code files, for a Stateflow chart. To do this, use the **RTW system code** options in the **Block parameters** dialog of the Stateflow chart (see “Nonvirtual Subsystem Code Generation” in the Real-Time Workshop documentation). You can control the names of the functions and the code files generated.

Conditional Input Branch Execution Optimization

This release introduces an optimization called conditional input branch execution, which speeds simulation and execution of code generated from the model.

Compatibility Considerations. Previously, when simulating models containing Switch or Multiport Switch blocks, Simulink executed all blocks required to compute all inputs to each switch at each time step. In this release, Simulink, by default, executes only the blocks required to compute the control input and the data input selected by the control input at each time step. Likewise, standalone applications generated from the model by the Real-Time Workshop software execute only the code needed to compute the control input and the selected data input. To explore this feature, see the demo `rtwdemo_condinput`.

Block Enhancements

- “New Rate Transition Block” on page 167
- “S-Function API Extended to Permit Users to Define DWork Properties” on page 168
- “Lookup Table Blocks Use New Run-Time Library for Smaller Code” on page 168
- “Relay Block Now Supports Frame-Based Processing” on page 168
- “Transport Delay and Variable Transport Delay Improvements” on page 169
- “Storage Classes for Data Store Memory Blocks” on page 169

New Rate Transition Block

In previous releases, Zero-Order Hold and Unit Delay blocks were required to handle problems of data integrity and deterministic data transfer between blocks having different sample rates.

The new Rate Transition block lets you handle sample rate transitions in multirate applications with greater ease and flexibility than the Zero-Order Hold and Unit Delay blocks.

The Rate Transition block handles both types of rate transitions (fast to slow, and slow to fast). When inserted between two blocks of differing sample rates, the Rate Transition block detects the two rates and automatically configures its input and output sample rates for the appropriate type of transition.

For more information on the use of the Rate Transition block with the Real-Time Workshop product, see “Sample Rate Transitions” in the Real-Time Workshop documentation. For a detailed description of the new block, see Rate Transition in the Simulink reference documentation.

S-Function API Extended to Permit Users to Define DWork Properties

The S-Function API has been extended to permit specification of an Real-Time Workshop identifier, storage class, and type qualifier for each DWork that an S-Function creates. The extensions consist of the following macros:

```
ssGetDWorkRTWIdentifier(S,idx)
ssSetDWorkRTWIdentifier(S,idx,val)
ssGetDWorkRTWStorageClass(S,idx)
ssSetDWorkRTWStorageClass(S,idx,val)
ssGetDWorkRTWTypeQualifier(S,idx)
ssSetDWorkRTWTypeQualifier(S,idx,val)
```

As is the case with data store memory or discrete block states, the Real-Time Workshop identifier may resolve against a `Simulink.Signal` object. An example has been added to `sfundemos`, in the miscellaneous category.

Lookup Table Blocks Use New Run-Time Library for Smaller Code

Lookup Table (2-D), Lookup Table (3-D), PreLook-Up Using Index Search, and Interpolation using PreLook-Up blocks now generate code that targets one of the many new specific, optimized lookup table operations in the Real-Time Workshop runtime library. This results in dramatically smaller code size. The library lookup functions themselves incorporate more enhancements to the actual lookup algorithms for speed improvements for most option settings, especially for linear interpolations.

Relay Block Now Supports Frame-Based Processing

Relay blocks can now handle frame-based input signals. Each row in a frame-based input signal is a separate set of samples in frames and each column represents a different signal channel. The block parameters should be scalars or row vectors whose length is equal to the number of signal channels. The block does not allow continuous frame-based input signals.

Transport Delay and Variable Transport Delay Improvements

Code generation for models containing the Transport Delay and Variable Transport Delay is now require less space.

Storage Classes for Data Store Memory Blocks

You can now control how Data Store Memory blocks in your model are stored and represented in the generated code, by assigning storage classes and type qualifiers. You do this in almost exactly the same way you assign storage classes and type qualifiers for block states. You can also associate a Data Store Memory block with a signal object, and control code generation for the block through the signal object.

See “Storage Classes for Data Store Memory Blocks” in the Real-Time Workshop documentation for more information.

Rapid Simulation Target Enhancement

Executables generated for the Rapid Simulation (RSim) target are now able to use any Simulink solver, including variable-step solvers. To use this feature, the target system must be able to check out a Simulink license when running the generated RSim executable.

For details, see Licensing Protocols for Simulink Solvers in RSim Executables in the Real-Time Workshop User’s Guide.

Compatibility Considerations

You can maintain backwards compatibility (that is, fixed-step solvers only, with no need to check out a Simulink license) by selecting **Use RTW fixed step solver** from the **Solver Selection** popup menu on the Rapid Simulation code generation options dialog. The default solver option is Auto, which will use the Simulink solver module only when the model requires it.

External Mode Enhancements

- Support for Rapid Simulation (RSim) target

The RSim target now includes full support for all features of Simulink external mode. External mode lets you use your Simulink block diagram as a front end for a target program that runs on external hardware or in a separate process on your host computer, and allows you to tune parameters and view or log signals as the target program executes.

- Support for ERT target

The Real-Time Workshop Embedded Coder software now includes full support for all features of Simulink external mode. External mode lets you use your Simulink block diagram as a front end for a target program that runs on external hardware or in a separate process on your host computer, and allows you to tune parameters and view or log signals as the target program executes.

- Support for uploading signals of all storage classes

Signals from all storage classes, including custom, can now be uploaded in external mode, as long as signals or parameters have addresses defined. For example, data stored as bit fields or `#defines` cannot be uploaded, but few other restrictions exist.

Simulink Data Object Enhancements

Simulink data objects include several new string properties that you can exploit for customizing code generation. These properties are

```
Simulink.Data.Description  
Simulink.Data.DocUnits  
RTWInfo.Alias
```

In this release, the Simulink engine and Target Language Compiler do not use these properties. The properties are included in the `model.rtw` file and are reserved for future use. `RTWInfo.Alias` defines the identifier to be used in place of the parent data object (parameter, signal, or state) in the code. The engine checks that the alias is uniquely used by only that object.

model.rtw Changes

In this release, a number of changes have been made to `model.rtw`.


Compatibility Considerations

If your applications depend on parsing `model.rtw` files using customized TLC scripts, read "model.rtw Changes Between Real-Time Workshop 5.0 and 4.1" in Appendix A of the Target Language Compiler documentation, which describes the structure and contents of compiled models.

Generate HTML Report Option Available for Additional Targets

In earlier releases, the **Generate HTML report** option was available only for the Real-Time Workshop Embedded Coder product. In the current release, the report is available for all targets (except the S-Function target and Rapid Simulation target).

The **Generate HTML report** option is located in the **General code generation options** category of the Real-Time Workshop page of the **Simulation Parameters** dialog box, as shown in the next figure.



The option is on by default. An abbreviated report is generated if you do not have the Real-Time Workshop Embedded Coder product installed.

Efficiency of Code Generated for GRT and GRT-Malloc Targets Improved

Substantial changes have been made to the GRT and GRT-Malloc targets to improve the efficiency of generated code.

Compatibility Considerations

If you have customized either type of target, you should make changes to your modified files to ensure that your target works properly with V5.0 (R13) of the Real-Time Workshop software.

You should begin with the versions of the target files included in this release, and introduce all of your existing customizations to them. If you are unable to follow this upgrade path, then perform all steps outlined in “Most Targets Use rtModel Instead of Root SimStruct” on page 163 and “Logging Code Moved to the Real-Time Workshop Library” on page 172.

Logging Code Moved to the Real-Time Workshop Library

All the support functions used for logging data have been moved from `rtwlog.c` to the Real-Time Workshop library.

Compatibility Considerations

If you have customized a GRT or GRT-Malloc Target, make the following changes to ensure compatibility with the new logging functions:

- Remove `rtwlog.c` from all of your template make files.
- In your target’s main C file (which was derived from `grt_main.c` or `grt_malloc_main.c`), include `rt_logging.h` instead of `rtwlog.h`.
- In your target’s main C file (which was derived from `grt_main.c` or `grt_malloc_main.c`), you need to change the calls to the logging related functions because the prototypes of these functions have changed. See `grt_main.c` (or `grt_malloc_main.c`) for the list of arguments that needs to be passed into each function.

Custom Code Blocks Moved from Simulink Library

The Custom Code blocks have been moved to a new library, named `custcode.mdl` (type `custcode` to access them).

Compatibility Considerations

Because custom code blocks are linked to this new library, backward compatibility is assured.

Target Language Compiler Changes

- `SPRINTF` built-in function added

A C-like `sprintf` formatting function has been added to the Target Language Compiler, which returns a TLC string encoded with data from a variable number of arguments.

`$assign str = SPRINTF(format,var,...)` formats the data in variable `var` (and in any additional variable arguments) under control of the specified `format` string, and returns a string variable containing the values. The function operates like C library `sprintf()`, except that output is the return value rather than contained in an argument to `sprintf`.

- `BlockInstanceData` function no longer available
- `%filescope` directive added

A new directive, `%filescope`, is now available for limiting scopes of variables to the files in which they are defined. All variables defined after the appearance of `%filescope` in a file have this property; otherwise, they default to global variables.

- Global variables `::` operator available

Use of the `::` operator to access global variables is now allowed in TLC files. Variables defined on the command line and records read from `model.rtw` files remain global variables. Nested include files cannot access variables local to the file that included them.

Compatibility Considerations

S-function TLC files should no longer use the `BlockInstanceData` function. All data used by a block should be declared using data type work vectors (DWork).

Documentation Enhancements

- The expression folding API is documented and available for you to use, particularly for writing inlined S-functions. In addition, expanded capabilities are available that support the TLC user control variable (ucv) in `%roll` directives, and enable expression folding for blocks such as Selector. See “Writing S-Functions That Support Expression Folding” in the Real-Time Workshop documentation for details.
- The *Real-Time Workshop User’s Guide* has been significantly updated and reorganized.
- Information pertaining to data structures and subsystems has been updated and made more accessible.
- New features and GUI changes have been documented
- A new *Real-Time Workshop Getting Started Guide* is available. This document explains basic Real-Time Workshop concepts, organizes tutorial material for easier access, and cross-references more detailed explanations in the User’s Guide.
- The Target Language Compiler documentation has been significantly updated and reorganized. A revised collection of tutorial examples provides new users with a more grounded introduction to TLC syntax. Documentation on the TLC Function Library and contents of `model.rtw` files has also been updated.

Fixed Bugs

- “ImportedExtern and ImportedExternPointer Storage Class Data No Longer Initialized” on page 176
- “External Mode Properly Handles Systems with no Uploadable Blocks” on page 176

- “Nondefault Ports Now Usable for External Mode on Tornado Platform” on page 176
- “Initialize Block Outputs Even If No Block Output Has Storage Class Auto” on page 176
- “Code Is Generated Without Errors for Single Precision Data Type Block Outputs” on page 177
- “Duplicate #include Statements No Longer Generated” on page 177
- “Custom Storage Classes Ignored When Unlicensed for the Real-Time Workshop® Embedded Coder Product” on page 177
- “Erroneous Sample Time Warning Messages No Longer Issued” on page 177
- “Discrete Integrator Block with Rolled Reset No Longer Errors Out” on page 177
- “Rate Limiter Block Code Generation Limitation Removed” on page 178
- “Multiport Switch with Expression Folding Limitation Removed” on page 178
- “Pulse Generator Code Generation Failures Rectified” on page 178
- “Stateflow I/O with ImportedExternPointer Storage Class Now Handled Correctly” on page 178
- “Parameters for S-Function Target Lookup Blocks May Now Be Made Tunable” on page 178
- “PreLookup Index Search Block Now Handles Discontiguous Wide Input” on page 179
- “SimViewingDevice Subsystem No Longer Fails to Generate Code” on page 179
- “Accelerator Now Works with GCC Compiler on UNIX” on page 179
- “Expression Folding Behavior for Action Subsystems Stabilized” on page 179
- “Dirty Flag No Longer Set During Code Generation” on page 179
- “Subsystem Filenames Now Completely Checked for Illegal Characters” on page 179

- “Sine Wave and Pulse Generator Blocks No Longer Needlessly Use Absolute Time” on page 180
- “Generated Code for Action Subsystems Now Correctly Guards Execution of Fixed in Minor Time Step Blocks” on page 180
- “Report Error when Code Generation Requested for Models with Algebraic Loops” on page 180

ImportedExtern and ImportedExternPointer Storage Class Data No Longer Initialized

The Real-Time Workshop build process now reverts to its previous behavior of not initializing data whose storage class is `ImportedExtern` or `ImportedExternPointer`. Such initialization is the external code’s responsibility.

External Mode Properly Handles Systems with no Uploadable Blocks

Connecting to systems with no blocks that can be uploaded in external mode used to fail and cause Simulink to act as though a simulation was running when none was. The only way to exit the model was to exit MATLAB. Connecting to these systems now will display a warning in the MATLAB command window and then run normally.

Nondefault Ports Now Usable for External Mode on Tornado Platform

In the prior release, a bug prevented the use of any but the default port to connect to a Tornado (VxWorks) target via external mode. The problem has been fixed and that configuration now works as documented.

Initialize Block Outputs Even If No Block Output Has Storage Class Auto

Previously, block outputs were initialized only if at least one block output had storage class `auto`. Now even if there are no `auto` Block I/O entries, exported globals and custom signals are initialized.

Code Is Generated Without Errors for Single Precision Data Type Block Outputs

In cases where a reused block outputs entry is the first single-precision data type block output in the full list of block outputs in the model, the Real-Time Workshop software now operates without reporting errors. See the Simulink Release Notes for related single-precision block enhancements.

Duplicate #include Statements No Longer Generated

The Real-Time Workshop build process now creates a unique list of C header files before emitting `#include` statements in the `model.h` file (formerly placed in `model_common.h`). For backwards compatibility, the old text buffering method for includes is still available for use, but can cause multiple includes in the generated code. You should update your custom code formats to use the `(S)LibAddToCommonIncludes()` functions instead of `LibCacheIncludes()`, which has been deprecated.

Custom Storage Classes Ignored When Unlicensed for the Real-Time Workshop Embedded Coder Product

If a user loads a model that uses custom storage classes, and the user is not licensed for the Real-Time Workshop Embedded Coder product, the custom storage class is ignored (storage class reverts to auto) and a warning is produced. Previously, this situation would have generated an error.

Erroneous Sample Time Warning Messages No Longer Issued

Erroneous warnings regarding sample times not being in the sample time table for models that contain a variable sample time block and a fixed step solver are no longer issued during model compilation.

Discrete Integrator Block with Rolled Reset No Longer Errors Out

The Simulink® Accelerator™ and Real-Time Workshop products used to error out if they had a Discrete Integrator block configured in 'ForwardEuler', non-level external reset, and the reset signal was a 'rolled' signal (having a width greater than 5). This has been fixed.

Rate Limiter Block Code Generation Limitation Removed

The Simulink Accelerator software now generates code for variable-step solver models that contain a rate limiter block inside an atomic subsystem.

Multiport Switch with Expression Folding Limitation Removed

The Simulink Accelerator and Real-Time Workshop products no longer generate a Fatal Error for Multiport Switch when expression folding is enabled.

Pulse Generator Code Generation Failures Rectified

Several problems with code generation for the pulse generator block have been eliminated:

- If the block type is PulseGenerator instead of Discrete PulseGenerator, code can now be generated.
- The scalar expansion for the delay variable is now correct.
- The start function for the Time-based mode in a variable-step solver now can generate code.

The first two problems also affected the Simulink Accelerator software.

Stateflow I/O with ImportedExternPointer Storage Class Now Handled Correctly

Stateflow input pointers for signals of ImportedExternPointer storage class are now correctly initialized, and no longer error out for charts producing output signals that are nonscalar and of ImportedExternPointer storage class.

Parameters for S-Function Target Lookup Blocks May Now Be Made Tunable

The S-Function target code will now compile for models having lookup and Lookup Table (2-D) blocks when parameters for those blocks are tunable.

PreLookup Index Search Block Now Handles Discontiguous Wide Input

The PreLookup Index Search block formerly only generated code for signals from the first roll region of discontiguous wide inputs, such as from a Max block. This has been fixed.

SimViewingDevice Subsystem No Longer Fails to Generate Code

Code generation no longer aborts for atomic subsystems configured with `SimViewingDevice=on`.

Accelerator Now Works with GCC Compiler on UNIX

The previous version of the Accelerator did not work when the user selected the gcc compiler with `mex -setup`. The Accelerator now supports using the gcc compiler on UNIX systems.

Expression Folding Behavior for Action Subsystems Stabilized

When a model contains an action subsystem (that is, a for loop or while iterator subsystem) and expression folding is enabled, invalid or inefficient code sometimes was generated for the model. This problem has been fixed.

Dirty Flag No Longer Set During Code Generation

In previous releases, a model would be marked as *dirty* during the code generation process and the status would be restored when the process was finished. With this release the model's dirty status does not change during code generation.

Subsystem Filenames Now Completely Checked for Illegal Characters

In previous releases, it was possible to specify a subsystem filename that contained illegal (non-alphanumeric) characters, if the name was long enough and the invalid characters were toward the end of the string. In this release this bug has been fixed, and the entire character string is now validated.

Sine Wave and Pulse Generator Blocks No Longer Needlessly Use Absolute Time

Previously, code generated for the Sine Wave and Pulse Generator blocks accessed absolute time when the blocks were configured as sample based. This access is not necessary and its overhead has been removed from the generated code.

Generated Code for Action Subsystems Now Correctly Guards Execution of Fixed in Minor Time Step Blocks

All blocks contained in an action subsystem must have the same rate unless some are continuous and some are fixed in minor step (“zoh continuous”). If there are both continuous and fixed in minor step blocks then the generated code needs to guard the code for the fixed in minor time step blocks to protect it from being executed in minor time steps.

These guards were not being generated causing some models to have wrong answers and consistency failures. This problem has been fixed and the guards are now generated.

This is also a fix for the Simulink Accelerator software.

Report Error when Code Generation Requested for Models with Algebraic Loops

The Real-Time Workshop software does not support models containing algebraic loops. V4.1 (R12.1) contained a bug that enabled some models having algebraic loops to generate code which could compute incorrect answers. The models affected were those containing no algebraic loops in their root level but having algebraic loops in one or more subsystems. This bug has been fixed, and now building these models will always cause an error to be reported.

Limitations for HP and IBM Platforms

The V4.0 (R12) Real-Time Workshop platform limitation for the HP and IBM® platforms still applies to V5.0 (R13). On the HP and IBM platforms, the Real-Time Workshop software opens the V3.0 (R11) **Tunable Parameters** dialog box in place of the **Model Parameter Configuration** dialog box.

Although they differ in appearance, both dialogs present the same information and support the same functionality.

Version 4.1 (R12.1) Real-Time Workshop Software

This table summarizes what's new in V4.1 (R12.1):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	Fixed bugs	No

New features and changes introduced in this version are

- “Block Reduction Option On by Default” on page 183
- “Buffer Reuse Code Generation Option” on page 183
- “Build Directory Validation” on page 184
- “Build Subsystem Enhancements” on page 184
- “C API for Parameter Tuning Documented” on page 184
- “Code Readability Improvements” on page 185
- “Support for Control Flow Blocks” on page 185
- “Expression Folding” on page 185
- “External Mode Enhancements” on page 186
- “Generate Comments Option” on page 186
- “Include System Hierarchy in Identifiers Option” on page 187
- “Rapid Simulation Target Support for Inline Parameters” on page 187
- “S-Function Target Enhancements” on page 187
- “Storage Classes for Block States” on page 188
- “Support for tilde (~) in Filenames on UNIX Platforms” on page 188
- “Target Language Compiler Enhancements” on page 188

- “RTWInfo Property Changed” on page 190
- “Fixed Bugs” on page 191

Note For information about closely related products that extend the Real-Time Workshop product, see the Release Notes for those products.

Block Reduction Option On by Default

The **Block reduction** option on the **Advanced** pane of the Simulation Parameters dialog box is now turned on by default.

Block reduction collapses certain groups of blocks into a single, more efficient block, or removes them entirely. This results in faster model execution during simulation and in generated code.

See “Reducing the Number of Blocks in a Model” in the Real-Time Workshop documentation for more information.

Compatibility Considerations

In previous releases, the **Block reduction** option on the **Advanced** pane of the Simulation Parameters dialog box was off by default. This option is now on by default.

Buffer Reuse Code Generation Option

A **Buffer reuse** option has been added to the **Real-Time Workshop** pane of the Simulation Parameters dialog box. When you select this option, the Real-Time Workshop software reuses signal storage whenever possible.

See “Reusing Memory Allocated for Signals” in the Real-Time Workshop documentation for more information.

Compatibility Considerations

In previous releases, the buffer reuse option was available only through MATLAB `set_param` and `get_param` commands, such as:

```
set_param(gcs, 'bufferreuse', 'on')
```

The ability to set and get this option with the `set_param` and `get_param` commands is still supported.

Build Directory Validation

The build process now disallows building programs in the MATLAB directory tree.

Compatibility Consideration

Prior to this release, the Real-Time Workshop software allowed you to build programs in the MATLAB directory tree. As of V4.1 (Release 12.1), this is no longer allowed. If you attempt to generate code in the MATLAB directory tree, the Real-Time Workshop software displays an error message, prompting you to change to a working directory that is not in the MATLAB directory tree. On a PC, you can continue to build in the directory `matlabroot/Work`.

The build process also prevents building programs when `matlabroot` has a dollar sign (\$) in its MATLAB directory name.

Build Subsystem Enhancements

The **Build Subsystem** feature, introduced in the Real-Time Workshop software V4.0 (R12), lets you generate code and build an executable from any nonvirtual subsystem within a model. In the Real-Time Workshop software V4.1 (R12.1), the **Build Subsystem** feature has been enhanced as follows:

- The **Build Subsystem** window now displays additional information about block parameters referenced by the subsystem.
- From the **Build Subsystem** window, you can now inline or set the storage class of any parameter.

See “Generating Code and Executables from Subsystems” in the Real-Time Workshop documentation for more information.

C API for Parameter Tuning Documented

The Real-Time Workshop software provides data structures and a C API that enable a running program to access model parameters without use of external mode.

To access model parameters via the C API, you generate a model-specific parameter mapping file, `model_pt.c`. This file contains parameter mapping arrays that contain information required for parameter tuning.

See “C API for Interfacing with Signals and Parameters” in the Real-Time Workshop documentation for information on how to generate and use the parameter mapping file.

Code Readability Improvements

Improvements to the readability of generated code include:

- Elimination of redundant parentheses.
- Long C statements in the generated code are now split across multiple lines.
- Block comments are more informative.

Support for Control Flow Blocks

Simulink V4.1 (R12.1) implements a number of blocks that support logic constructs such as if-else and switch, and looping constructs such as do-while, for, and while. The Real-Time Workshop software V4.1 (R12.1) introduces code generation support for these blocks.

For more information on the control flow blocks, see “Modeling Control Flow Logic” in the Simulink documentation.

Expression Folding

Expression folding is a code optimization technique that minimizes the computation of intermediate results at block outputs, and the storage of such results in temporary buffers or variables. Wherever possible, the Real-Time Workshop software collapses, or “folds,” block computations into single expressions, instead of generating separate code statements and storage declarations for each block in the model.

Expression folding dramatically improves the efficiency of generated code, frequently achieving results that compare favorably to hand-optimized code. In many cases, model computations fold into a single highly optimized line of code.

Most Simulink blocks support expression folding.

For more information, see “Minimizing Computations and Storage for Intermediate Results” in the Real-Time Workshop documentation.

External Mode Enhancements

- Support for inline parameters

The Real-Time Workshop software now lets you use the **Inline parameters** code generation option when building an external mode target program. When you inline parameters, you can use the **Model Parameter Configuration** dialog box to remove individual parameters from inlining and declare them to be tunable. This allows you to improve overall efficiency by inlining most parameters, while at the same time retaining the flexibility of runtime tuning for selected parameters that are important to your application. In addition, the **Model Parameter Configuration** dialog box offers you options for controlling how parameters are represented in the generated code.

Each time Simulink connects to a target program that was generated with **Inline parameters** on, the target program uploads the current value of its tunable parameters (if any) to the host. These values are assigned to the corresponding MATLAB workspace variables. This procedure ensures that the host and target are synchronized with respect to parameter values.

All targets that support external mode (that is, `grt`, `grt_malloc`, and Tornado) now allow inline parameters.

See “External Mode Communications Overview” in the Real-Time Workshop documentation for more information.

- New status bar display

When Simulink is connected to a running external mode target program, the simulation time and other status bar information is now displayed and updated just as it would be in normal mode.

Generate Comments Option

A new **Comments** option has been added to the **Real-Time Workshop** pane of the Simulation Parameters dialog box. This option lets you control whether

or not comments are written in the generated code. See “Configuring Code Comments” in the Real-Time Workshop documentation for more information.

Include System Hierarchy in Identifiers Option

A new **Include system hierarchy in identifiers** option has been added to the **Real-Time Workshop** pane of the Simulation Parameters dialog box. When you select this option, the Real-Time Workshop software inserts system identification tags in the generated code (in addition to tags included in comments). The tags help you to identify the nesting level, within your source model, of the block that generated a given line of code.

See “How Symbols Are Formatted in Generated Code” in the Real-Time Workshop documentation for more information.

Rapid Simulation Target Support for Inline Parameters

The Rapid Simulation (RSim) Target now works with **Inline parameters** on. Note that when **Inline parameters** is on, the storage class for all parameters and signals is silently forced to auto.

S-Function Target Enhancements

The S-Function Target **Generate S-function** feature, introduced in the Real-Time Workshop software V4.0 (R12), lets you generate an S-function from a subsystem. This feature has been enhanced as follows:

- The **Generate S-function** window now displays additional information about block parameters referenced by the generating subsystem.
- If you have installed and licensed the Real-Time Workshop Embedded Coder product, the **Generate S-function** window lets you invoke the Real-Time Workshop Embedded Coder build process to generate an S-function wrapper.

See “Automated S-Function Generation” in the Real-Time Workshop documentation for details.

Storage Classes for Block States

For certain block types, the Real-Time Workshop software lets you control how block states in your model are stored and represented in the generated code. Using the **State Properties** dialog, you can:

- Control whether or not states declared in generated code are interfaceable (visible) to externally written code. You can also specify that signals are to be stored in locations declared by externally written code.
- Assign symbolic names to block states in generated code.

For more information, see “Block State Storage and Interfacing” in the Real-Time Workshop documentation.

Support for tilde (~) in Filenames on UNIX Platforms

All filename fields in Simulink now support the mapping of the tilde (~) character in filenames. For example, in a To File block you can specify `<code>~/outdir/file.mat</code>`. On most systems, this expands to `/home/$USER/outdir/file.mat`. The Real-Time Workshop software uses the expanded names.

Target Language Compiler Enhancements

This section summarizes Target Language Compiler enhancements.

- New TLC debugger added

The TLC debugger helps you identify programming errors in your TLC code. You can set breakpoints in your TLC code, execute TLC code line-by-line, examine and change variables, and perform many other useful operations.

The TLC debugger operates during code generation, incurring almost no overhead in the code generation process. You can invoke the debugger:

- By selecting options in the **TLC debugging options** category of the **Real-Time Workshop** pane.
- By including `%breakpoint` statements in your TLC file.
- By using the MATLAB `tlc` command, as in

```
tlc -dc <options>
```


- By using the `-dc` build option in the **System target file** field of the **Real-Time Workshop** pane.

For more information, see “Debugging TLC Files” in the Target Language Compiler documentation.

- `model.rtw` file format changed

The format of the `model.rtw` file has changed.

- Block I/O connection handling cleaned up

The handling of signal connections in `rtw/c/tlc/blkio.lib.tlc` and `rtw/ada/tlc/blkio.lib.tlc` has been reworked. See the description of `LibBlockInputSignal` in the Target Language Compiler documentation for details.

- Support for literal string added

If a string constant is preceded by an `L` format specifier (as in `L"string"`), the Target Language Compiler performs no escape character processing on that string. This is useful for specifying PC-style paths without using double back slash characters.

```
%addincludepath L"C:\mytlc"
```

The following examples are equivalent.

- `L"d:\this\is\a\path"`
- `"d:\\this\\is\\a\\path"`

- Library functions added

The following functions have been added to the TLC Function Library:

```
LibBlockInputSignalConnected
LibBlockInputSignalLocalSampleTimeIndex
LibBlockInputSignalOffsetTime
LibBlockInputSignalSampleTime
LibBlockInputSignalSampleTimeIndex
LibBlockOutputSignalOffsetTime
LibBlockOutputSignalSampleTime
LibBlockOutputSignalSampleTimeIndex
LibBlockMatrixParameterBaseAddr
```

LibBlockParameterBaseAddr
LibBlockNonSampledZC

See the Target Language Compiler documentation for information on these functions.

Compatibility Considerations

- *model.rtw* file format has changed. For more information, see the Target Language Compiler documentation.
- `BlockTypeSetup` and `BlockInstanceSetup` calls have been reordered. During the initialization phase of code generation, the Target Language Compiler makes a pass over all blocks in the model and executes several functions, including:
 - Each block's `BlockTypeSetup` function the first time that block type is encountered.
 - Each block's `BlockInstanceSetup` function. `BlockInstanceSetup` is called for all instances of a given block type in the model.

The order in which these calls are made is significant, because the `BlockInstanceSetup` function may depend upon global variables that are initialized by the `BlockTypeSetup` function.

In V4.1 (R12) , the `BlockTypeSetup` function is called before the `BlockInstanceSetup`. This corrects a problem in previous releases, where `BlockInstanceSetup` was erroneously called first. You may need to change your S-functions or block implementations if they depend upon the previous behavior.

RTWInfo Property Changed

Changes have been made to the `RTWInfo` property of `Simulink.Signal` and `Simulink.Parameter` data objects.

Compatibility Considerations

In V4.0 (R12), the `RTWInfo` class had a `TypeQualifier` property, corresponding to the **RTW storage type qualifier** field of signal ports and parameters.

The Real-Time Workshop software V4.1 (R12.1) now supports creation of custom storage classes, removing the need for the `TypeQualifier` property. You should use custom storage classes when type qualification is needed.

By default, the `TypeQualifier` property of `RTWInfo` objects is no longer visible in the Simulink Data Explorer. Also, the `TypeQualifier` property is no longer written to `ObjectProperties` records in the `model.rtw` file. For backward compatibility, the `TypeQualifier` property remains active. You can set and retrieve the property through a direct reference. For example,

```
Kp.RTWInfo.TypeQualifier = 'const'
```

or

```
tq = Kp.RTWInfo.TypeQualifier
```

You can make the `TypeQualifier` property visible in the Simulink Data Explorer for the duration of a MATLAB session. To do this, execute the following command prior to opening the Simulink Data Explorer,

```
feature('RTWInfoTypeQualifier',1)
```

The above command also directs the Real-Time Workshop software to include the `TypeQualifier` property in `ObjectProperties` records in the `model.rtw` file.

For more information see “Simulink Data Objects and Code Generation” in the Real-Time Workshop documentation.

Fixed Bugs

The Real-Time Workshop software V4.1 (R12) includes the following bug fixes.

Block Reduction Crash Fixed

A problem that crashed MATLAB due to a segmentation fault during the block reduction process has been fixed. This problem occurred only if the **Block Reduction** option was on, and if a Scope block was connected to a block that was removed due to block reduction.

Build Subsystem Gives Better Error Message for Function Call Subsystems

The **Build Subsystem** feature does not currently support triggered function-call subsystems. The Real-Time Workshop software now gives a more informative error message when a **Build Subsystem** is attempted with a triggered function-call subsystem.

Check Consistency of Parameter Storage Class and Type Qualifier

The Real-Time Workshop software now checks for consistency of parameter storage class and type qualifier when a parameter is specified by both the Model Parameter Configuration dialog and a referenced Simulink data object.

Code Optimization for Unsigned Saturation and DeadZone Blocks

When the lower limit of a Saturation or DeadZone block is a zero and is nontunable, and the data type is unsigned, the comparison against the lower limit is omitted from the code. Similarly, if the upper or lower limit of the Saturation block is nontunable and nonfinite, the comparison against the infinite limit is omitted.

Correct Code Generation of Fixed-Point Blockset Blocks in DSP Blockset Models

A code generation bug involving some DSP Blockset blocks (see list below) was fixed. When these blocks were driven by a block from the Fixed-Point Blockset, generated code would write outside array memory bounds. The following DSP Blockset blocks generated incorrect code:

- Delay Line
- Frame Status Conversion
- Matrix Multiply
- Multipoint Selector
- Pad
- Submatrix
- Window Function
- Zero Pad

Correct Compilation with Green Hills and DDI Compilers

Compilation errors for files associated with matrix inversion in the *matlabroot/rtw/c/libsrc* directory were fixed. These errors occurred with the Green Hills® and DDI compilers.

Fixed Build Error with Models Having Names Identical to Windows NT Commands

This fix prevents an error that occurred when building models having names identical to Windows NT® internal commands. Examples would be models named `verify` or `path`. Such model names are now allowed.

Fixed Error Copying Custom Code Blocks

An error in the Custom Code block `CopyFcn` callback was fixed. The problem caused an error when copying a custom code block within a model.

Fixed Error in `commonmaplib.tlc`

A typo in rev 1.17 of `commonmap.tlc` was fixed. This typo caused an error during code generation, when using the `grt_malloc` target with **External mode** selected.

Fixed Name Clashes with Run-Time Library Functions

The Real-Time Workshop software now uses the macros `rt_min` and `rt_max` to avoid clashing with run-time library `min` and `max` functions.

Improved Handling of Sample Times

The sample time handling for the S-function and ERT targets has been improved to use the compiled sample time instead of the user specified sample time on the input port blocks.

Look-Up Table (n-D) Code Generation Bug Fix

The Real-Time Workshop software now generates correct code for Look-Up Table (n-D) blocks having 5 or more dimensions with different dimension sizes.

Parenthesize Negative Numerics in Fcn Block Expressions

Fcn block expressions in the generated code failed to compile in the case of a unary operator preceding a workspace variable with a negative value, such as the expression

```
-v*u
```

Such expressions are now enclosed in parentheses, as in

```
(-v) * u
```

Unnecessary Warnings and Declarations Removed from Generated Code

Several unnecessary warnings and declarations in the generated code have been removed. These include:

- In functions where the `tid` argument is not referenced, the declaration

```
(void)tid
```

is no longer generated. (The `tid` argument is required because the function API is predefined.)

- Warnings involving `const` casts were suppressed in some of the `rtw/c/libsrc` modules.

Retain .rtw File Option Now Works in Accelerator Mode

In previous releases, the **Retain .rtw file** option (on the TLC Debugging Options page of the **Simulation Parameters** dialog) was ignored if Simulink was in Accelerator mode. Now, you can retain the `model.rtw` file during a build, regardless of the simulation mode.

S-Function Target Memory Allocation Bug Fix

A segmentation fault during generation of S-functions was removed by fixing the memory management of the port data structure.

TLC Bug Fixes

- Fixed a bug where local variables of calling functions were sometimes incorrectly visible to called functions.
- The ISINF, ISNAN, and ISFINITE functions now work for complex values.
- The %filescope directive now works as documented.
- Zero indexing on complex numbers is now supported.

In prior releases, the Target Language Compiler allowed 0 indexing for integer and real values, but not for complex values. This restriction has been removed in the Target Language Compiler 4.1, as shown in the following example.

```
%assign a = 1.0 + 3.0i
%assign b = a[0] %% zero index now allowed
```

- Fixed a crash that occurred if ROLL_ITERATIONS was called outside of a %roll construct. ROLL_ITERATIONS returns NULL if called outside of a %roll construct.
- TLC now allows use of any path separator character independent of operating system. You can use either \ or / as a path separator character on UNIX or Microsoft Windows).
- Fixed a bug in the compare for equality operation. 0.0 now compares equal to -0.0.

Version 4.0 (R12) Real-Time Workshop Software

This table summarizes what's new in V4.0 (R12):

New Features and Changes	Version Compatibility Considerations	Fixed Bugs and Known Problems	Related Documentation at Web Site
Yes Details below	Yes—Details labeled as Compatibility Considerations , below. See also Summary.	No bug fixes	No

New features and changes introduced in this version are

- “New Real-Time Workshop® Embedded Coder Product” on page 197
- “Support for Simulink Data Objects” on page 197
- “Support for ASAP2 Data Files” on page 198
- “Enhanced Real-Time Workshop Configuration Pane” on page 198
- “Other User Interface Enhancements” on page 198
- “Support for New Simulink Advanced Options Pane” on page 198
- “Model Parameter Configuration Dialog Box” on page 199
- “Support for Tunable Expressions” on page 199
- “S-Function Target Enhancements” on page 200
- “External Mode Enhancements” on page 200
- “Build Directory” on page 201
- “Code Optimization Features” on page 202
- “Subsystem Code Generation” on page 203
- “Nonvirtual Subsystem Code Generation” on page 203
- “Standard Filename Extensions for Generated Files” on page 204
- “hilite_system and Code Tracing” on page 204

- “Generation of Parameter Comments” on page 205
- “Borland 5.4 Compiler Support” on page 205
- “Enhanced Makefile Include Path Rules” on page 205
- “Column-Major Matrix Ordering” on page 205
- “S-Function Target MEX-Files Must Be Rebuilt” on page 206
- “Target Language Compiler Enhancements” on page 206

New Real-Time Workshop Embedded Coder Product

Real-Time Workshop Embedded Coder software is a new add-on product that replaces and enhances the Embedded Real-Time (ERT) target.

See the Real-Time Workshop Embedded Coder documentation for details.

Compatibility Considerations

The new Real-Time Workshop Embedded Coder product is 100% compatible with the ERT target. In addition to supporting all previous functions of the ERT target, the new Real-Time Workshop Embedded Coder product includes many enhancements.

Support for Simulink Data Objects

The Real-Time Workshop software supports Simulink data objects. Simulink provides the built-in `Simulink.Parameter` and `Simulink.Signal` classes for use with the Real-Time Workshop software. Using these classes, you can create parameter and signal objects and assign storage classes and storage type qualifiers to the objects. These properties control how the generated code represents signals and parameters. You can extend the `Simulink.Parameter` and `Simulink.Signal` classes to include user-defined properties.

See “Simulink Data Objects and Code Generation” in the Real-Time Workshop documentation for details.

Support for ASAP2 Data Files

ASAP2 is a data definition standard proposed by the Association for Standardization of Automation and Measuring Systems (ASAM). This standard is used for data measurement, calibration, and diagnostic systems.

The Real-Time Workshop software now lets you export an ASAP2 file containing information about your model during the code generation process. See “Generating ASAP2 Files” in the Real-Time Workshop documentation for details.

Enhanced Real-Time Workshop Configuration Pane

The **Real-Time Workshop** pane of the Simulation Parameters dialog box has been reorganized and made easier to use. See “Configuring Real-Time Workshop Code Generation Parameters” in the Real-Time Workshop documentation for details.

Other User Interface Enhancements

- The **Tools** menu of the Simulink model window contains a new **Real-Time Workshop** submenu with shortcuts to frequently used features.
- You can now select a target configuration from the System Target File Browser by double-clicking on the desired entry in the target list.

See the Real-Time Workshop documentation for details.

Compatibility Considerations

The double-click mechanism for selecting a target configuration from the System Target File Browser does not replace the previous selection method. You can still select a target entry and then click **OK**.

Support for New Simulink Advanced Options Pane

An **Advanced** pane options pane has been added to the Simulation Parameters dialog box. The **Advanced** pane contains

- New code generation options

- Options formerly located in the **Diagnostics** pane
- Options formerly located in the **Real-Time Workshop** pane

Compatibility Considerations

Simulation Parameters dialog box options formerly located in the **Diagnostics** and **Real-Time Workshop** panes have been relocated to the new **Advanced** pane.

Model Parameter Configuration Dialog Box

The **Model Parameter Configuration** dialog box extends and replaces the **Tunable Parameters** dialog box. The **Model Parameter Configuration** dialog box enables you to

- Declare individual parameters to be tunable
- Control the generated storage declarations for each parameter

See “Parameter Storage, Interfacing, and Tuning” in the Real-Time Workshop documentation for details.

Compatibility Considerations

You must now use the **Model Parameter Configuration** dialog box instead of the **Tunable Parameters** dialog box to declare tunable parameters.

Support for Tunable Expressions

A tunable expression is an expression that contains one or more tunable parameters. Tunable expressions are now supported during simulation and in generated code.

Tunable expressions are allowed in masked subsystems. You can use tunable parameter names or tunable expressions in a masked subsystem dialog box. When referenced in lower-level subsystems, such parameters remain tunable.

See “Tunable Expressions” in the Real-Time Workshop documentation for a detailed discussion on using tunable parameters in expressions.

S-Function Target Enhancements

S-function target enhancements include:

- Support for variable-step solvers
- Supports for tunable parameters
- New **Generate S-function** menu option on the Simulink Tools menu that lets you automatically generate an S-function from a subsystem

The S-function target is now documented in “S-Function Target” in the Real-Time Workshop documentation.

External Mode Enhancements

New features have been added to external mode:

- Signal Viewing Subsystems have been implemented to let you encapsulate processing and viewing of signals received from the target system. Signal Viewing Subsystems run only on the host, generating no code in the target system. This is useful in situations where you want to process or condition signals before viewing or logging them, but you do not want to perform these tasks on the target system. See “Signal Viewing Subsystems” in the Real-Time Workshop documentation for details.
- The external mode communications application program interface (API) is now documented. If you want to implement external mode communications via your own low-level protocol, see “Creating an External Mode Communication Channel” in the Real-Time Workshop documentation.
- The **External Signal & Triggering** dialog box has been enhanced as indicated in the compatibility considerations listed below.
- As indicated in the compatibility considerations listed below, several additional features now support external mode.

Compatibility Considerations

Previously, you could use only Scope blocks in external mode to receive and view signals uploaded from the target program. The following features now support external mode:

- The default operation of the **External Signal & Triggering** dialog box has been changed to make monitoring a target program simpler. See “External Signal Uploading and Triggering” in the Real-Time Workshop documentation for details.
- Previously, you could use only Scope blocks to receive and view signals uploaded from a target program. The following features now support external mode
 - Dials & Gauges Blockset
 - Display blocks
 - To Workspace blocks
 - Signal Viewing Subsystems
 - S-functionsSee “External Mode Compatible Blocks and Subsystems” in the Real-Time Workshop documentation for details.

Build Directory

The Real-Time Workshop build process now creates a *build directory* within your working directory. The build directory stores generated source code and other files created during the build process. The Real-Time Workshop software derives the build directory name, *model_target_rtw*, from the name of the source model and the chosen target.

See “Directories Used During the Build Process” in the Real-Time Workshop documentation for details.

Compatibility Considerations

If you have created custom targets for the Real-Time Workshop software under Release 11, you must update your custom system target files and template makefiles to create and utilize the build directory. See `matlabroot/rtw/c/grt` for examples.

To update a Release 11 target:

- 1 Add the following to your system target file.

```

/%
BEGIN_RTW_OPTIONS
.
.
.
rtwgensettings.BuildDirSuffix = '_grt_rtw';
END_RTW_OPTIONS
%/

```

- 2 Add ".." to the INCLUDES rule in your template makefile. The following example is from grt_lcc.tmf.

```
INCLUDES = -I. -I.. $(MATLAB_INCLUDES) $(USER_INCLUDES)
```

The first -I. gets files from the build directory, and the second -I.. gets files (e.g., user written S-functions) from the current working directory.

Conceptually, think of the current directory and the build directory as the same (as it was in Release 11). The current working directory contains items like user written S-functions. The reason ".." must be added to the INCLUDES rule is that make is invoked in the build directory (i.e., the current directory was temporarily moved).

- 3 Place the generated executable in your current working directory. The following example is from grt_lcc.tmf.

```

PROGRAM = ../$(MODEL).exe
$(PROGRAM) : $(OBJS) $(RTWLIB)
$(LD) $(LDFLAGS) -o $@ $(LINK_OBJS) $(RTWLIB) $(LIBS)

```

Code Optimization Features

This section describes new or modified code generation options that are designed to help you optimize your generated code. The options described are located on the **Advanced** pane of the Simulation Parameters dialog box.

- **Block reduction:** When selected, Simulink collapses certain groups of blocks into a single, more efficient block, or removes them entirely. This results in faster model execution during simulation and in generated code.

- **Parameter pooling:** When selected, Simulink optimizes memory usage when multiple block parameters refer to storage locations that are separately defined but structurally identical.
- **Signal storage reuse:** Replaces the (Enable/Disable) **Optimized block I/O storage** option. See the compatibility considerations below for details.

See “Optimizing a Model for Code Generation” in the Real-Time Workshop documentation for more information on code optimization.

Compatibility Considerations

The **Signal storage reuse** option replaces the (Enable/Disable) **Optimized block I/O storage** option of previous releases. **Signal storage reuse** is functionally identical to the older option. Turning **Signal storage reuse** on is equivalent to enabling **Optimized block I/O storage**.

Subsystem Code Generation

The Real-Time Workshop software now generates code and builds an executable from any subsystem within a model. The build process uses the code generation and build parameters of the root model. See “Generating Code and Executables from Subsystems” in the Real-Time Workshop documentation for details.

Nonvirtual Subsystem Code Generation

The Real-Time Workshop software now lets you generate code modules at the subsystem level. This feature applies only to nonvirtual subsystems. With nonvirtual subsystem code generation, you control how many files are generated, as well as the file and function names. To set options for nonvirtual subsystem code generation, you use the subsystem’s **Block Parameters** dialog box.

See “Nonvirtual Subsystem Code Generation” in the Real-Time Workshop documentation for details.

Compatibility Considerations

Nonvirtual subsystem code generation replaces the **Function management** code generation options available in previous releases. Nonvirtual subsystem

code generation is a more general and flexible mechanism for controlling the number and size of generated files than the **Function management** code generation options, **File splitting** and **Function splitting**.

Standard Filename Extensions for Generated Files

The Real-Time Workshop software now generates source code and header files that have standard filename extensions — .c and .h.

Compatibility Considerations

In previous releases, the Real-Time Workshop software gave some generated files special filename extensions, such as .prm or .reg. As of this release, the Real-Time Workshop software generates source code and header files that have standard filename extensions. The file naming conventions for the following generated files have changed:

File	Old Filename	New Filename
Model registration file	<i>model.reg</i>	<i>model_reg.h</i>
Model parameter file	<i>model.prm</i>	<i>model_prm.h</i>
BlockIOSignals structure file	<i>model.bio</i>	<i>model_bio.c</i>
ParameterTuning file	<i>model.pt</i>	<i>model_pt.c</i>
External mode data type transition file	<i>model.dt</i>	<i>model_dt.c</i>

If your application code uses `#include` statements to include the Real-Time Workshop software generated files (such as *model.prm*), you may need to modify these statements. See “Files Created During Build Process” in the Real-Time Workshop documentation.

hilite_system and Code Tracing

The Real-Time Workshop software uses a new command, `hilite_system`, to write system/block identification tags in the generated code. The tags are designed to help you identify the block, in your source model, that generated a given line of code.

For more information on identification tags and code tracing, see “Tracing Generated Code Back to Your Simulink Model”.

Compatibility Considerations

In previous releases, the Real-Time Workshop software used the `locate_system` command to trace a tag back to the generating block. The Real-Time Workshop software now uses the new `hilite_system` command to trace identification tags instead of `locate_system`. Starting with this release, use the `hilite_system` command to trace a tag back to the generating block.

Generation of Parameter Comments

The **Force generation of parameter comments** option in the **General code generation options** section of the **Real-Time Workshop** pane of the Simulink Parameters dialog box controls the generation of comments in the model parameter structure (rtP) declaration in `model_prm.h`. This lets you reduce the size of the generated file for models with a large number of parameters.

Borland 5.4 Compiler Support

The Real-Time Workshop software now supports Version 5.4 of the Borland C/C++ compiler.

Enhanced Makefile Include Path Rules

Two new rules and macros have been added to Real-Time Workshop template makefiles. These rules let you add source and include directories to makefiles generated by the Real-Time Workshop software without having to modify the template makefiles themselves. This feature is useful if you need to include your code when building S-functions.

Column-Major Matrix Ordering

The Real-Time Workshop software now uses column-major ordering for two-dimensional signal and parameter data instead of row-major ordering.

Compatibility Considerations

In previous releases, the Real-Time Workshop software used row-major ordering for two-dimensional signal and parameter data. The Real-Time Workshop software now uses column-major ordering.

If your hand-written code interfaces to such signals or parameters via `ExportedGlobal`, `ImportedExtern`, or `ImportedExternPointer` declarations, review any code that relies on row-major ordering, and make appropriate revisions.

S-Function Target MEX-Files Must Be Rebuilt

Compatibility Considerations

S-function MEX-files generated by the S-function target under V3.0 (R11) are not compatible with V4.0 (R12). The incompatibilities are due to new features, such as parameter pooling.

If you have built S-function MEX-files with the S-function target under V3.0 (R11), you must rebuild them. See “S-Function Target” in the Real-Time Workshop documentation for more information.

Target Language Compiler Enhancements

The Target Language Compiler has been enhanced as follows:

- TLC file parsed before execution

The Target Language Compiler now completes parsing of the TLC file just before execution. This aids development because syntax errors are caught the first time the TLC file is run instead of the first time the offending line is reached.

- Speed enhanced

The Target Language Compiler features speed improvements throughout the software. In particular, the speed of block parameter generation has been enhanced.

- Build directory created and used

The Target Language Compiler now creates and uses a build directory. The build directory is in the current directory and prevents generated code from clashing with other files generated for other targets, and keeps your model directories maintenance to a minimum.

- Profiler added

A new profiler has been added to the Target Language Compiler to help you find performance problems in TLC code.

- *model.rtw* changes

This release contains a new format and changes to the *model.rtw* file and the size of the file has been reduced.

- Block parameter aliases added

Aliases have been added for block parameters in the *model.rtw* file.

- Text expansion improved

TLC contains new, flexible methods for text expansion from within strings.

- Column-major ordering used

Two-dimensional signal and parameter data now use column-major ordering.

- Record handling improved

TLC now utilizes new record data handling.

- Language semantics changed

- Improved EXISTS behavior.
- New TLC primitives for record handling.
- Functions can return records.
- Records can be printed.
- Records can be empty.
- Record aliases are available.
- Records can be expanded with %<>.
- Built-in functions cannot be undefined via %undef.

- Short circuit evaluation for Boolean operators, `%if-%elseif-%endif`, and `?:` expressions are handled properly
- Conversions of values to and from MATLAB.
- Enhanced conversion rules for FEVAL. You can now pass records and structs to FEVAL.
- Relational operators can be used with nonfinite values.
- Loop control variables are local to loop bodies.
- Built-in functions added

The following built-in functions have been added to the language:

```
FIELDNAMES
GENERATE_FORMATTED_VALUE
GETFIELD
ISALIAS
ISEMPTY
ISEQUAL
ISFIELD
REMOVEFIELD
SETFIELD
```

- Built-in values added

The following built-in values have been added to the language:

```
INTMAX
INTMIN
TLC_FALSE
TLC_TRUE
UINTMAX
```

- Support for inlined code added
Support has been added for two-dimensional signals in inlined code.

Compatibility Considerations

If you are upgrading from Release 11 to Release 12, the following changes may affect your TLC code:

- Nested evaluations are no longer supported. Expressions such as the following are no longer supported:

```
%<LibBlockParameterValue(%<myVariable>," ", " ", " ")>
```

You must convert these expressions into equivalent non-nested expressions.

- Aliases are no longer automatically created for Parameter blocks while reading in the Real-Time Workshop files.
- You cannot change the contents of a "Default" record after it has been created. In the previous TLC, you could change a "Default" record and see the change in all the records that inherited from that default record.
- The %codeblock and %endcodeblock constructs are no longer supported.
- %defines and macro constructs are no longer supported.
- Use of line continuation characters (. . . and \) are not allowed inside of strings. Also, to place a double quote (") character inside a string, you must use \". Previously, the Target Language Compiler allowed you to use "" to get a double quote in a string.
- Semantics have been formalized to %include files in different contexts (e.g., from generate files, inside of %with blocks, etc.) %include statements are now treated as if they were read in from the global scope.
- The previous the Target Language Compiler had the ability to split function definitions (and other directives) across include file boundaries (e.g., you could start a %function in one file and %include a file that had the %endfunction). This no longer works.
- Nested functions are no longer allowed. For example,

```
%function foo ()
    %function bar ()
    %endfunction
%endfunction
```

- Built-in functions cannot be undefined via %undef. It is possible to undefine built in values, but this practice is not encouraged.
- Recursive records are no longer allowed. For example,

```
Record1 {
```

```

    Val    2
    Ref    Record2
  }
Record2  {
  Val    3
  Ref    Record1
}

```

- Record declaration syntax has changed. The following code fragments illustrate the differences between declaring a record `recVar` in previous versions of the Target Language Compiler and the current release.

- Previous versions:

```

%assign recVarAlias = recVar { ...
  field1 value1 ...
  field2 value2 ...
  ...
  fieldN valueN ...
}

```

- Current version:

```

%createrecord recVar { ...
  field1 value1 ...
  field2 value2 ...
  ...
  fieldN valueN ...
}

```

- Semantics of the `EXISTS` function have changed. In the previous release of TLC, `EXISTS(var)` would check if the variable represented by the string value in `var` existed. In the current release of TLC, `EXISTS(var)` checks to see if `var` exists or not.

To emulate the behavior of `EXISTS` in the previous release, replace

```
EXISTS(var)
```

with

```
EXISTS("%<var>")
```


Compatibility Summary for Real-Time Workshop Software

This table summarizes new features and changes that might cause incompatibilities when you upgrade from an earlier version, or when you use files on multiple versions. Details are provided in the description of the new feature or change.

Version (Release)	New Features and Changes with Version Compatibility Impact
Latest Version V7.3 (R2009a)	See the Compatibility Considerations subheading for each of these new features or changes: <ul style="list-style-type: none"> • “New Compilation Report for emlc” on page 7
V7.2 (R2008b)	See the Compatibility Considerations subheading for each of these new features or changes: <ul style="list-style-type: none"> • “Support for Simulink Legacy Code Tool Enhancement” on page 13 • “Improperly-Scaled Fixed-Point Relational Operators Now Match MATLAB Results” on page 15 • “MISRA C Code Initialization Enhancements” on page 17 • “Configure Unique Custom Code Settings for Library Models in the Configuration Parameters Dialog Box” on page 19
V7.1.1 (R2008a+)	None
V7.1 (R2008a)	See the Compatibility Considerations subheading for each of these new features or changes: <ul style="list-style-type: none"> • “emlc Searches Directories in Different Order” on page 25 • “Generated Code No Longer Automatically Includes math.h Header File” on page 26 • “Default TCP/IP Transport for External Mode Uses New Server (Target) Side Communication Interface” on page 27
V7.0.1 (R2007b+)	None

Version (Release)	New Features and Changes with Version Compatibility Impact
V7.0 (R2007b)	<p>See the Compatibility Considerations subheading for each of these new features or changes:</p> <ul style="list-style-type: none"> • “Code Generation from Embedded MATLAB Algorithms That Span Multiple M-Files” on page 32 • “New Configuration Parameters for Controlling Compiler Optimization Level and Specifying Custom Optimization Settings” on page 33 • “Real-Time Workshop Reserved Keywords Listed in Documentation” on page 40 • “Template Makefile Token ADD_MDL_NAME_TO_GLOBALS Removed” on page 40 • “Nonzero Start Time Behavior Change” on page 40 • “TLC Custom Code Library Function Behavior Changes” on page 41 • “Template Makefile MAKECMD Path Change for gmake on Microsoft Windows” on page 42
V6.6.1 (R2007a+)	None
V6.6 (R2007a)	<p>See the Compatibility Considerations subheading for this new feature or change:</p> <ul style="list-style-type: none"> • “New sl_customization Based Method for Registering External Mode Transport Layers” on page 51
V6.5 (R2006b)	<p>See the Compatibility Considerations subheading for each of these new features or changes:</p> <ul style="list-style-type: none"> • “Code Formatting Consistency Improvements” on page 56 • “Change to Default Settings for Multitasking Diagnostic Options” on page 57 • “Parameter Pooling Is Now Always Enabled” on page 58
V6.4.1 (R2006a+)	None

Version (Release)	New Features and Changes with Version Compatibility Impact
V6.4 (R2006a)	<p>See the Compatibility Considerations subheading for each of these new features or changes:</p> <ul style="list-style-type: none"> • “Format Enhancements for model.rtw File” on page 69 • “Changes to TLC Files in matlabroot/rtw/c/tlc” on page 72
V6.3 (R14SP3)	<p>See the Compatibility Considerations subheading for each of these new features or changes:</p> <ul style="list-style-type: none"> • “Customizations to Built-In Blocks” on page 77 • “Use slbuild Instead of rtwgen” on page 77 • “Model Hardware Configuration Parameters Now Honor Device Type Restrictions” on page 78 • “rem Function No Longer Supports Tunable Arguments” on page 79
V6.2.1 (R14SP2+)	None
V6.2 (R14SP2)	None
V6.1 (R14SP1)	None
V6.0 (R14)	<p>See the Compatibility Considerations subheading for each of these new features or changes:</p> <ul style="list-style-type: none"> • “Support for New Simulink Model Referencing (Model Block) Feature” on page 100 • “New C API for Accessing Model Block Outputs and Parameter Data” on page 103 • “Back-Propagating Auto, Test-pointed Signal Labels Through Subsystem Output Ports” on page 105 • “Declaring Wide Signals, States, and Parameters as ImportedExternPointer” on page 105 • “External Mode Changes May Impact Customized Makefiles and Static Main files” on page 108 • “Upgrading Custom Transport Layers for External Mode to Single-Channel Architecture” on page 110

Version (Release)	New Features and Changes with Version Compatibility Impact
	<ul style="list-style-type: none"> • “Preventing User Source Code from Being Deleted from Build Directories” on page 113 • “Hook Files Describing Hardware Characteristics No Longer Supported” on page 114 • “New Asynchronous Block Library” on page 119 • “Symbol Formatting Options Replaced” on page 129 • “Global Data Structure Identifiers for Targets Now Incorporate Model Name” on page 131 • “Hardware Configuration Parameters” on page 133 • “Defining and Displaying Custom Target Options” on page 134 • “New SelectCallback Function for System Target Files” on page 136 • “Shared Utilities Directory and the Build Process” on page 136 • “Tornado Target Requires Macro in Template Make File” on page 139 • “Custom Storage Classes Can No Longer Be Used with GRT Targets” on page 140 • “Accessing the Number of Sample Times from TLC for Custom Targets” on page 142 • “TLCFILES Built-In Now Returns Full Path to Model File Rather Than Relative Path” on page 142
V5.1.1 (R13SP1+)	<p>See the Compatibility Considerations subheading for this new feature or change:</p> <ul style="list-style-type: none"> • “Error Resulting from Inaccessible Signal Reporting No Longer Reported” on page 146
V5.1 (R13SP1)	None
V5.0.1 (R13+)	None

Version (Release)	New Features and Changes with Version Compatibility Impact
V5.0 (R13)	<p>See the Compatibility Considerations subheading for each of these new features or changes:</p> <ul style="list-style-type: none"> • “Comments Not Generated for Reduced Blocks When "Show eliminated statements" Is Off” on page 153 • “Code for Nonvirtual Subsystems Is Now Reusable” on page 158 • “Packaging of Generated Code Files Simplified” on page 160 • “Different Required Files for S-Function Deployment” on page 162 • “Most Targets Use rtModel Instead of Root SimStruct” on page 163 • “Hook Files Required for Communicating Target-specific Word Characteristics” on page 165 • “Code Generation Unified for Real-Time Workshop and Stateflow Products” on page 166 • “Conditional Input Branch Execution Optimization” on page 166 • “model.rtw Changes” on page 170 • “Efficiency of Code Generated for GRT and GRT-Malloc Targets Improved” on page 172 • “Logging Code Moved to the Real-Time Workshop Library” on page 172 • “Custom Code Blocks Moved from Simulink Library” on page 173 • “Target Language Compiler Changes” on page 173
V4.1 (R12+)	<p>See the Compatibility Considerations subheading for each of these new features or changes:</p> <ul style="list-style-type: none"> • “Block Reduction Option On by Default” on page 183 • “Buffer Reuse Code Generation Option” on page 183 • “Build Directory Validation” on page 184 • “Target Language Compiler Enhancements” on page 188

Version (Release)	New Features and Changes with Version Compatibility Impact
	<ul style="list-style-type: none"> • “RTWInfo Property Changed” on page 190
V4.0 (R12)	<p>See the Compatibility Considerations subheading for each of these new features or changes:</p> <ul style="list-style-type: none"> • “New Real-Time Workshop® Embedded Coder Product” on page 197 • “Other User Interface Enhancements” on page 198 • “Support for New Simulink Advanced Options Pane” on page 198 • “Model Parameter Configuration Dialog Box” on page 199 • “External Mode Enhancements” on page 200 • “Build Directory” on page 201 • “Code Optimization Features” on page 202 • “Nonvirtual Subsystem Code Generation” on page 203 • “Standard Filename Extensions for Generated Files” on page 204 • “hilite_system and Code Tracing” on page 204 • “Column-Major Matrix Ordering” on page 205 • “S-Function Target MEX-Files Must Be Rebuilt” on page 206 • “Target Language Compiler Enhancements” on page 206